

# **Dell EMC OpenManage Operations Connector for Micro Focus Operations Bridge Manager Version 2.0.1**

## **Installation Guide**

## Notes, cautions, and warnings

 **NOTE:** A NOTE indicates important information that helps you make better use of your product.

 **CAUTION:** A CAUTION indicates either potential damage to hardware or loss of data and tells you how to avoid the problem.

 **WARNING:** A WARNING indicates a potential for property damage, personal injury, or death.

<b>Chapter 1: Introduction.....</b>	<b>4</b>
<b>Chapter 2: Installation prerequisites.....</b>	<b>5</b>
Supported devices.....	5
<b>Chapter 3: Installing and upgrading OpenManage Operations Connector for Micro Focus OBM.....</b>	<b>6</b>
Download and install Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1.....	6
Upgrade OpenManage Operations Connector for Micro Focus OBM.....	6
<b>Chapter 4: Post installation.....</b>	<b>8</b>
Configure OME connection parameters.....	8
Configure Task Scheduler parameters.....	9
Activate Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 policies.....	9
Activate Topology Integration policy.....	9
Activate the Event Integration policy.....	10
Activate node count information policy.....	10
Create custom view in Micro Focus Operations Bridge Manager console.....	11
Configure OME URL tool.....	11
<b>Chapter 5: Repair Dell EMC OpenManage Operations Connector for Micro Focus OBM.....</b>	<b>13</b>
Repair program feature using the installer.....	13
Repair program feature using Windows Control Panel.....	13
<b>Chapter 6: Uninstalling Dell EMC OpenManage Operations Connector for Micro Focus OBM.....</b>	<b>14</b>
Deactivate and delete policies.....	14
Uninstall Dell EMC OpenManage Operations Connector for Micro Focus OBM using the installer.....	15
Uninstall Dell EMC OpenManage Operations Connector for Micro Focus OBM using Windows Control Panel.....	15
<b>Chapter 7: Accessing support content from the Dell EMC support site.....</b>	<b>16</b>

# Introduction

The Dell EMC OpenManage Operations Connector for Micro Focus Operations Bridge Manager (OBM) enables the integration of OpenManage Essentials and OpenManage Enterprise (OME) with Micro Focus OBM. The Operations Connector for OME helps system and IT administrators to get a comprehensive view of the Dell EMC devices in a data center by collecting the systems management data about the events and topology from OpenManage Enterprise or OpenManage Essentials, and transferring it to the Micro Focus OBM. It also enables you to launch OME directly from the Micro Focus OBM environment to troubleshoot, configure, and manage activities for the Dell EMC devices.

The Operations Connector enables you to create a connection between OME environment for life-cycle management of the Dell EMC devices and Business Service Management in Micro Focus OBM by providing the following:

- Synchronization of Topology information from OME to Micro Focus OBM
- Synchronization of Event information from OME to Micro Focus OBM

The Operations Connector for OME installer, installation guide, and release notes are packaged in the self-extracting executable **Dell EMC OpenManage Operations Connector Micro Focus OBM v2.0.1\_A00.exe** file. Before installing this version of Operations Connector for OME, Dell EMC recommends to download the latest documents from [dell.com/openmanagemanuals](http://dell.com/openmanagemanuals) or [dell.com/omconnectionsEnterpriseSystemsManagement](http://dell.com/omconnectionsEnterpriseSystemsManagement).

This document provides information about the software and system requirements, the steps to install, upgrade and uninstall Dell EMC OpenManage Operations Connector for Micro Focus Operations Bridge Manager v2.0.1.

## Installation prerequisites

The requirements for installing the Dell EMC OpenManage Operations Connector for Micro Focus OBM are as follows:

- Local administrator privilege on the Micro Focus OBM server.
- Minimum of 10 GB free hard disk space available on the Micro Focus OBM server.

### Operating System requirements

**Table 1. Operating System requirements**

Components	Supported Versions	Operating Systems supported
Micro Focus Operations Bridge Manager	2020.10	Windows Server 2016 Datacenter Edition
Micro Focus Operations Connector	2019.05	Windows Server 2019 Datacenter Edition
Dell EMC OpenManage Essentials	2.5	See the OpenManage Essentials and OpenManage Enterprise Support Matrix available at <a href="https://dell.com/openmanagemanuals">dell.com/openmanagemanuals</a> .
Dell EMC OpenManage Enterprise	3.1 and above	NA

 **NOTE:** It is recommended to install OME and Operations Connector for Micro Focus OBM on separate host systems.

#### Topics:

- [Supported devices](#)

### Supported devices

The Dell EMC Operations Connector for Micro Focus OBM supports all the Dell EMC devices that are supported by OME. For detailed information about the supported Dell EMC devices, see the *OpenManage Essentials or OpenManage Enterprise Support Matrix* at [dell.com/openmanagemanuals](https://dell.com/openmanagemanuals).

# Installing and upgrading OpenManage Operations Connector for Micro Focus OBM


The following section provides steps to upgrade and install Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1

## Topics:

- [Download and install Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1](#)
- [Upgrade OpenManage Operations Connector for Micro Focus OBM](#)

## Download and install Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1

1. Download the Operations Connector for Micro Focus OBM available at [dell.com/support](https://dell.com/support)  
The installer is packaged as **Dell EMC OpenManage Operations Connector Micro Focus OBM v2.0.1\_A00.exe** file.
2. Unzip the **Dell EMC OpenManage Operations Connector Micro Focus OBM v2.0.1\_A00.exe** file on the Operations Connector for Micro Focus OBM server.  
The following files are unzipped:
  - Dell EMC OpenManage Operations Connector Micro Focus OBM v2.0.1.exe file.
  - Dell EMC OpenManage Operations Connector Micro Focus OBM v2.0.1\_IG.pdf file.
  - Dell EMC OpenManage Operations Connector Micro Focus OBM v2.0.1\_ReadMe.txt file.
3. Run **Dell EMC OpenManage Operations Connector Micro Focus OBM v2.0.1.exe** file from the directory where the files are unzipped.
 

 **NOTE:** If Operations Connector for Micro Focus OBM is not installed, an error message is displayed to install the Operations Connector for Micro Focus OBM.
4. On the **Welcome** page, click **Next**.
5. Select the Dell EMC End-user License Agreement (EULA) and, click **Next**.
6. Click **Install**.
7. After the installation is complete, click **Finish**.

## Upgrade OpenManage Operations Connector for Micro Focus OBM

This section describes about the steps to upgrade Dell EMC OpenManage Operations Connector for Micro Focus OBM Version 2.0 to Dell EMC OpenManage Operations Connector for Micro Focus OBM Version 2.0.1.

If Micro Focus Operation Connector 2019.05 is not installed, ensure to upgrade to 2019.05 before upgrading OpenManage Connector for Micro Focus OBM.

To upgrade Dell EMC OpenManage Operations Connector for Micro Focus OBM Version 2.0 to Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1, follow these steps:

1. Download the Operations Connector for Micro Focus OBM installer available at [dell.com/support](https://dell.com/support)  
The OME installer is packaged as **Dell EMC OpenManage Operations Connector Micro Focus v2.0.1\_A00.exe** file.

2. On the Operations Connector for Micro Focus OBM, unzip the **Dell EMC OpenManage Operations Connector\_Micro\_Focus\_OBM\_v2.0.1\_A00.exe** file.

The following files are unzipped:

- Dell EMC OpenManage Operations Connector\_Micro\_Focus\_OBM\_v2.0.1.exe file.
- Dell EMC OpenManage Operations Connector\_Micro\_Focus\_OBM\_v2.0.1\_IG.pdf file.
- Dell EMC OpenManage Operations Connector\_Micro\_Focus\_OBM\_v2.0.1\_ReadMe.txt file.

3. Navigate to the directory where the file is unzipped and run **Dell EMC OpenManage Operations Connector\_Micro\_Focus OBM\_v2.0.1.exe** file. You are prompted with the following message: **An older version of the product is already installed. Would you like to upgrade to a newer version?**
4. Click **Yes** .
5. Click **Next**.
6. Select the **Dell EMC End-user License Agreement (EULA)** and click **Install**.
7. After the upgrade is completed, click **Finish**.

# Post installation

Perform the following steps after installing Operations Connector for OME:

## Topics:

- [Configure OME connection parameters](#)
- [Configure Task Scheduler parameters](#)
- [Activate Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 policies](#)
- [Create custom view in Micro Focus Operations Bridge Manager console](#)
- [Configure OME URL tool](#)

## Configure OME connection parameters

After installing Operations Connector for OME, configure OME connection parameters using the configuration utility.

To configure the OME parameters such as OME hostname, domain name, user name, password, and port number, perform the following steps:

1. On the Micro Focus OBM Operations Connector server, go to %OvDataDir%\conf\DellEMCBsmIntOME\scripts.

**NOTE:** <OvDataDir> is the data directory of Micro Focus OBM Operations Agent. The <OvDataDir> default value for the windows operating system is **C:\ProgramData\HP\HP BTO Software**.

2. Run the following command-line arguments as a local administrator:

```
configureBsmConnectorForOME.bat [-username <username> -password <password> -hostname <hostname> -domain <domain> -port <port> -consoletype <consoletype>]
```

Example:

```
configureBsmConnectorForOME.bat -username admin -password Password@123 -hostname 111.101.26.08 -port 2607 -consoletype OMEssentials
```

```
configureBsmConnectorForOME.bat -username admin -password Password@123 -hostname 111.101.26.08 -port 443 -consoletype OMEnterprise
```

-username: To configure the OME user name.

The maximum length of the username is 20 characters.

-password: To configure the OME password.

-hostname: To configure the OME hostname or IP.

-domain: To configure the OME domain name.

-port: To configure the OME port number.

**NOTE:** Allowed range for port number is between 1–65535.

-consoletype: To configure the OME Console type.

**NOTE:** Options are OMEssentials and OMEnterprise.

**NOTE:** Ensure to have appropriate access to OME user ID so that the API query fetches device inventory data.

**NOTE:** For OME user-specific information, see the OpenManage Essentials and OpenManage Enterprise User Guide at [dell.com/omconnectionsEnterpriseSystemsManagement](http://dell.com/omconnectionsEnterpriseSystemsManagement) or [dell.com/openmanagemanuals](http://dell.com/openmanagemanuals)




# Configure Task Scheduler parameters


The following are the Task Schedulers to configure after installing the Operations Connector for OME:

- Dell EMC Event Scheduler—Collects Topology information from OME
- Dell EMC Topology Scheduler—Collects Event information from OME

To configure the Task Scheduler parameters, perform the following steps:

1. On the Micro Focus OBM Operations connector server, open **Task Scheduler**.
2. Select **Task Scheduler Library** on the left pane.
3. On the right pane, see the following tasks:
  - **Dell EMC Event Scheduler**
  - **Dell EMC Topology Scheduler**
4. Double-click on Topology Scheduler and Event Scheduler.  
**Properties** window is displayed for each of the tasks. On the **Properties** window, perform the following:
  - a. In **General** tab, under the **Security options**, select **Run whether user is logged on or not** option.
  - b. Click **OK**.
  - c. Enter user login credentials.

 **NOTE:** If you are configuring Dell EMC Event and Dell EMC Topology Scheduler tasks for the first time, ensure to run the Task Scheduler manually.
5. Click **OK**.
6. Right-click on each tasks and click **Run**.


 **NOTE:** Ensure both Dell EMC Event Scheduler and Dell EMC Topology Scheduler are running.

## Activate Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 policies

To populate devices, events, and node count information from OME to Micro Focus OBM console, it is necessary to activate the Operations Connector for OME policies. For more information about policies, see Dell EMC OpenManage Operations Connector for Micro Focus OBM policies in *Dell EMC OpenManage Operations Connector Micro Focus OBM User Guide* at [dell.com/support](https://dell.com/support) go to **All Products > Software > Enterprise System Management > OpenManage Operations Connector for Micro Focus OBM**.

Following are the Operations Connector for OpenManage Enterprise and OpenManage Essentials policies:

1. [Dell EMC OpenManage Operations Connector for MicroFocus OBM v2.0.1- Topology Integration..](#)
2. [Dell EMC OpenManage Operations Connector for MicroFocus OBM v2.0.1-Node Count Information..](#)
3. [Dell EMC OpenManage Operations Connector for MicroFocus OBM v2.0.1-Event Integration.](#)


 **NOTE:** Since Adobe Flash player is End Of Life, operations connector command line tools is used for policy management.


## Activate Topology Integration policy

Activate the Topology Integration policy in the Dell EMC OpenManage Operations Connector for Micro Focus OBM for periodic Topology synchronization of Dell EMC devices between OME and Micro Focus OBM.

To activate the Topology Integration policy, perform the following steps:

1. Navigate to %OvDataDir%\datafiles\policymanagement\store directory.

 **NOTE:** <OvDataDir> is the data directory of MicroFocus OBM Operations agent. The <OvDataDir> default value for the windows operating system is C:\ProgramData\HP\HP BTO Software.
2. Open the Topology Integration policy file (39587549-6c59-4377-91e5-01fec8f55a54\_data).
3. If any changes is required for polling interval, change the value of **interval** parameter as required and save the file.

 **NOTE:** The default value for **interval** is set to **24h0m0s** which is 24 hours.

**NOTE:** It is recommended not to change any parameters except the **interval** in Topology Integration policy file.

**NOTE:** Ensure that the polling interval of the Topology Integration policy and trigger interval of the Topology Scheduler task are same.

4. Open a Command Prompt window as an administrator and change the current directory to %OvDataDir%\installation\HPOprBSMC.
5. Run the following command `bsmc-policy.bat --list`. This lists all the policies with their Name, Policy ID and other details.
6. To activate the policy, run the following command `bsmc-policy.bat -activate -id 39587549-6c59-4377-91e5-01fec8f55a54` by providing the appropriate Policy ID
7. To verify if the policy is activated, run the following command `bsmc-policy.bat --list` **Activation State** for Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 - Topology Integration policy should be **active**.

## Activate the Event Integration policy

Activate the Event Integration policy in the Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 periodic synchronization of events associated with the Dell EMC devices between OME and Micro Focus OBM

To activate the Event Integration policy, perform the following steps:

1. Navigate to %OvDataDir%\datafiles\policymanagement\store directory.

**NOTE:** <OvDataDir> is the data directory of Micro Focus OBM Operations Agent. The <OvDataDir> default value for the windows operating system is C:\ProgramData\HP\HP BTO Software
2. Open the Event Integration policy file(a09bceb7-1b42-4305-8097-8f95e76f90cf\_data).
3. If any changes is required for polling interval, change the value of **interval** parameter as required and save the file.

**NOTE:** The default value for **interval** is set to **5m** which is **5 minutes**.

**NOTE:** Ensure that the trigger interval of the Event Scheduler task is twice the polling interval of the Event Integration policy.
4. To ensure that the events forwarded to the Micro Focus OBM console display the correct timestamp, modify the value of **TIMECREATED** in Event Integration policy file(a09bceb7-1b42-4305-8097-8f95e76f90cf\_data).
  - a. Open the Event Integration policy file(a09bceb7-1b42-4305-8097-8f95e76f90cf\_data)
  - b. The default value for **TIMECREATED** is <\$DATA:/event/Time>. Change this value based on the time zone of Operation Connector setup. For example, if time zone is ahead of UTC by 05:30 hours, modify the **default value** <\$DATA:/event/Time> to <\$DATA:/event/Time> +5.5

**NOTE:** It is recommended not to change any parameters except the **interval** and **TIMECREATED** in Event Integration policy file.
5. Open a Command Prompt window as an administrator and change the current directory to %OvDataDir%\installation\HPOprBSMC
6. Run the following command `bsmc-policy.bat --list`. This will list all the policies with their Name, Policy ID and other details.
7. To activate the policy, run the following command `bsmc-policy.bat -activate -id a09bceb7-1b42-4305-8097-8f95e76f90cf` by providing the appropriate Policy ID
8. To verify if the policy is activated, run the following command `bsmc-policy.bat --list`. **Activation State** for Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 - Event Integration policy should be **active**

## Activate node count information policy

Activate the node count information policy to view the number of nodes collected after Topology information are made available to MicroFocus OBM

To activate the node count information policy, perform the following steps:

1. Open a command prompt window as an administrator and change the current directory to %OvDataDir%\installation\HPOprBSMC

**NOTE:** <OvDataDir> is the data directory of Micro Focus OBM Operations Agent. The <OvDataDir> default value for the windows operating system is C:\ProgramData\HP\HP BTO Software.

2. Run the following command `bsmc-policy.bat --list`. This will list all the policies with their Name, Policy ID and other details.
3. To activate the policy, run the following command `bsmc-policy.bat -activate -id d735337d-11a0-4c31-9d7a-114861e29141` by providing the appropriate Policy ID.
4. To verify if the policy is activated, run the following command `bsmc-policy.bat --list`. **Activation State** for Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 - Node Count Information policy should be **active**


## Create custom view in Micro Focus Operations Bridge Manager console

A custom view in the Micro Focus Operations Bridge Manager console is created:

- To view all Dell EMC devices along with associated events.
- To view Dell EMC infrastructure information transferred from the Dell domain manager (OME). This helps in managing the devices effortlessly.
- To perform necessary actions such as to close events, to launch respective tool, and so on for active events.

To create a custom view in Micro Focus OBM, perform the following steps:

1. In the Micro Focus OBM console, open **Administration > RTSM Administration > Modeling > Modeling Studio**.
2. Click **Resources**.  
Resources tab is displayed along with CI Selector and CI Types.
3. In **Resource Type** field, select **Models** from the drop-down list.  
On the left pane, **CiCollections** list is displayed.
4. Right-click OME host name or OME IP, and select **Open Model**.  
On the right pane, view the device hierarchy associated with the selected OME host name or OME IP address.

 **NOTE:** Ensure to select the same OME host name or OME IP address that was provided while configuring OME connection parameters in [Configure OME connection parameters](#) on page 8.


5. Right-click the OME host name (top node), and then click **Generate view for selected model**.
6. In **Creating New View** window, select **Content only - including links** from **Available Perspectives** pane, and then move it to **Selected Perspectives** pane.
7. Click **OK**.  
The **Perspective\_Based\_View\_x** window is created, where 'x' is a variable.
8. Click **Save**.  
The **Save Perspective Based View** window is displayed.
9. In the **View Name** field, enter the desired name, and then click **OK**.

For information about viewing the Dell EMC devices in the Micro Focus console, see the section Viewing the devices in Micro Focus OBM console in the *Dell EMC OpenManage Operations Connector for Micro Focus OBM User Guide* at [dell.com/omconnectionsEnterpriseSystemsManagement](https://dell.com/omconnectionsEnterpriseSystemsManagement) or [dell.com/openmanagemanuals](https://dell.com/openmanagemanuals)


## Configure OME URL tool


By configuring the OME URL tool, enables you to launch the OME web console from Micro Focus OBM to troubleshoot, configure, and manage activities for the Dell EMC devices.


To configure the OME URL tool, perform the following steps:

1. On Micro Focus console, click **Administrator > Operations Console > Tools**.
2. On the left pane, click **ConfigurationItem > InfrastructureElement**
3. On the right pane, click  and select URL.  
The **CREATE URL TOOL** is displayed.
4. In the **CREATE URL TOOL** window:
  - a. Enter the value in **Display Name** field.
  - b. Select **Category** as **Default Category**.
  - c. In **URL** field, enter OME URL in the format—`https://<OME IP address or OME FQDN>:<OME Port Number>`.

For example, `https://100.109.27.99:2809`.

 **NOTE:** The default port number for OpenManage Essentials is 2607.

 **NOTE:** The default port number for OpenManage Enterprise is 443.

 **NOTE:** If you have provided a different port number while installing OME, then ensure to provide the same port number while creating OME URL.

- d. Click **Test** to verify OME console launch.  
The OME console is successfully launched.
- e. Click **Create**.

# Repair Dell EMC OpenManage Operations Connector for Micro Focus OBM

Repair option is used when files are missing or corrupted and can be replaced by using any one of the following options:

- [OpenManage Operations Connector for Micro Focus OBM installer](#)
- [Windows Control Panel](#)

## Topics:

- [Repair program feature using the installer](#)
- [Repair program feature using Windows Control Panel](#)

## Repair program feature using the installer

In this topic you will learn on repairing features using installer.

To repair the corrupted or missing files using the installer, perform the following steps:

1. On the Operations Connector for Micro Focus OBM server, browse the location where the files are extracted.
2. Double-click the **Dell EMC OpenManage Operations Connector\_Micro\_Focus\_OBM\_v2.0.1.exe** file.
3. In the **Welcome** screen, click **Next**.
4. In the **Program Maintenance** screen, select **Repair**, and then click **Next**.
5. Click **Install** and then click **Finish**.

The **Dell EMC OpenManage Operations Connector for Micro Focus OBM Version 2.0.1** is successfully repaired.

## Repair program feature using Windows Control Panel

In this topic, you will learn how to repair features using windows control panel

To repair the corrupted or missing files using the Windows Control Panel, perform the following steps:

1. From the **Start** menu, click **Control Panel > Programs > Uninstall a program**.
2. In the **Uninstall or change a program** window, click **Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1**, and then click **Repair** to initiate the repair process.

The **Dell EMC OpenManage Operations Connector for Micro Focus v2.0.1** is successfully repaired.

# Uninstalling Dell EMC OpenManage Operations Connector for Micro Focus OBM

## Before uninstalling the Operations Connector for OME

1. Ensure to deactivate and delete the Operations Connector for OME policies manually:
  - Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1- Topology Integration policy.
  - Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1- Node Count Information policy.
  - Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1- Event Integration policy.

For information about deactivating and deleting policies, see [Deactivating and deleting the policies](#).

Upon successful deactivation and deletion of policies, uninstall the Operations Connector for OME using:

- OpenManage Operations Connector for Micro Focus OBM installer.
- Windows Control Panel.


## Topics:

- [Deactivate and delete policies](#)
- [Uninstall Dell EMC OpenManage Operations Connector for Micro Focus OBM using the installer](#)
- [Uninstall Dell EMC OpenManage Operations Connector for Micro Focus OBM using Windows Control Panel](#)

## Deactivate and delete policies

Following are the steps to deactivate the policies:

1. Open a Command Prompt window as an administrator and change the current directory to %OvDataDir%\installation\HPOprBSMC
2. Run the following command `bsmc-policy.bat --list` This will list all the policies with their Name, Policy ID and other details.
3. Deactivate the policies by using the command as mentioned below:
  - a. To deactivate Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 - Topology Integration policy. Run `bsmc-policy.bat -deactivate -id 39587549-6c59-4377-91e5-01fec8f55a54`
  - b. To deactivate Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 - Event Integration policy. Run `bsmc-policy.bat -deactivate -id a09bceb7-1b42-4305-8097-8f95e76f90cf`
  - c. To deactivate Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1 - Node Count Information policy. Run `bsmc-policy.bat -deactivate -id d735337d-11a0-4c31-9d7a-114861e29141`

 **NOTE:** Since Adobe Flash player is End Of Life, operations connector command line tools is used for policy management.

4. To verify if the policy is de-activated, run the following command `bsmc-policy.bat --list`. **Activation State** for all the policies should be **deactivate**.

Delete the policies by following below steps:

5. Navigate to %OvDataDir%\datafiles\policymanagement\store directory
6. Delete below files:
  - a. 39587549-6c59-4377-91e5-01fec8f55a54\_data
  - b. 39587549-6c59-4377-91e5-01fec8f55a54\_header.xml
  - c. a09bceb7-1b42-4305-8097-8f95e76f90cf\_data
  - d. a09bceb7-1b42-4305-8097-8f95e76f90cf\_header.xml
  - e. d735337d-11a0-4c31-9d7a-114861e29141\_data
  - f. d735337d-11a0-4c31-9d7a-114861e29141\_header.xml

# Uninstall Dell EMC OpenManage Operations Connector for Micro Focus OBM using the installer

To remove the Operations Connector for OME using the installer:

1. On the Micro Focus OBM Operations server, go to the location where the installer is unzipped.
2. Double-click the **Dell EMC OpenManage Operations Connector\_Micro Focus OBM\_v2.0.1.exe** file.
3. On the **Welcome** screen, click **Next**.
4. On the **Program Maintenance** screen, select **Remove**, and then click **Next**.
5. To uninstall the connector, follow the instructions on the screen.  
The **Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1** is successfully uninstalled.

# Uninstall Dell EMC OpenManage Operations Connector for Micro Focus OBM using Windows Control Panel

To remove the Operations Connector for OME using the Windows Control Panel:

1. From the **Start** menu, click **Control Panel > Programs > Uninstall a program**.  
The **Uninstall a program window** is displayed.
2. Click **Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1**, and then click **Uninstall**.  
The **Programs and Features** window is displayed.
3. Click **Yes**.  
The **Dell EMC OpenManage Operations Connector for Micro Focus OBM v2.0.1** is successfully uninstalled.

# Accessing support content from the Dell EMC support site

Access supporting content related to an array of systems management tools using direct links, going to the Dell EMC support site, or using a search engine.

- Direct links:
  - For Dell EMC Enterprise Systems Management and Dell EMC Remote Enterprise Systems Management—<https://www.dell.com/esmmanuals>
  - For Dell EMC Virtualization Solutions—<https://www.dell.com/SoftwareManuals>
  - For Dell EMC OpenManage—<https://www.dell.com/openmanagemanuals>
  - For iDRAC—<https://www.dell.com/idracmanuals>
  - For Dell EMC OpenManage Connections Enterprise Systems Management—<https://www.dell.com/OMConnectionsEnterpriseSystemsManagement>
  - For Dell EMC Serviceability Tools—<https://www.dell.com/serviceabilitytools>
- Dell EMC support site:
  1. Go to <https://www.dell.com/support>.
  2. Click **Browse all products**.
  3. From the **All products** page, click **Software**, and then click the required link.
  4. Click the required product and then click the required version.

Using search engines, type the name and version of the document in the search box.