

IBM Maximo Asset Management
Version 7 Release 6.1

Installation Guide
(IBM WebSphere)



Note

Before using this information and the product it supports, read the information in “Notices” on page 153.

This edition applies to version 7, release 6, modification 1, fix pack 0 of IBM Maximo Asset Management and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright IBM Corporation 2007, 2018.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Chapter 1. Preparing for installation . . . 1

Software installation images	1
Installation program overview	1
Configuration program overview	1

Chapter 2. Automatically configuring middleware during deployment. . . . 3

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment	4
Installing Db2 v11.1 using the Maximo Asset Management version 7.6.1 installation program.	5
Installing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management version 7.6.1 Installation Manager.	6
Preparing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management configuration program	7
Running the Maximo Asset Management 7.6.1 installation program	8
Configuring Maximo Asset Management version 7.6.1 using the Maximo Asset Management version 7.6.1 configuration program	9
Creating the NOTF JMS queue	9
Creating the NOTFERR JMS queue	10

Chapter 3. Automatically configuring existing middleware during deployment 13

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment	14
Preparing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management configuration program	14
Running the Maximo Asset Management 7.6.1 installation program	15
Configuring Maximo Asset Management version 7.6.1 using the Maximo Asset Management version 7.6.1 configuration program	16
Creating the NOTF JMS queue	16
Creating the NOTFERR JMS queue	17

Chapter 4. Manually configuring existing middleware during deployment 19

Maximo Asset Management installation with manual middleware configuration.	20
Manual configuration of the database.	21
Manually configuring Db2 v11.1	21
Manually configuring Microsoft SQL Server 2012.	23
Manual configuration of the directory server	25
Manually configuring IBM Security Directory Server	26

Manually configuring Microsoft Active Directory version 2012.	30
Manual configuration of the J2EE server.	32
Manually configuring WebSphere Application Server Network Deployment	32
Running the Maximo Asset Management 7.6.1 installation program	58
Configuring Maximo Asset Management version 7.6.1 with manually configured middleware	59
Creating the NOTF JMS queue	60
Creating the NOTFERR JMS queue	61

Chapter 5. Update the application database with the UpdateDB Lite command 63

Updating the database with UpdateDB Lite	63
--	----

Chapter 6. Deploying in a cluster environment 65

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment	66
Installing Db2 v11.1 using the Maximo Asset Management version 7.6.1 installation program	67
Installing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management version 7.6.1 Installation Manager	68
Preparing WebSphere Application Server Network Deployment and configuring application server cluster profiles using the Maximo Asset Management configuration program	69
Configuring cluster members on additional WebSphere Application Server Network Deployment nodes	71
Running the Maximo Asset Management 7.6.1 installation program	72
Configuring Maximo Asset Management in a cluster environment using the Maximo Asset Management configuration program.	73

Chapter 7. Silent installation 75

Creating silent response files for installation	75
Sample silent installation response files	76
Updating password values in silent response files	77
Silently installing the Installation Manager software	77
Silently installing Maximo Asset Management and related middleware.	78
Silently uninstalling Maximo Asset Management and related middleware	79

Chapter 8. Silent configuration 81

Creating silent response files for middleware configuration	81
---	----

Sample silent middleware configuration response files	81
Creating a response file for silent Maximo Asset Management configuration	82
Silently configuring middleware	83
Silently configuring Maximo Asset Management	83
Silently remove middleware configuration	84
Remove product configuration silently	84

Chapter 9. Configuring the HTTPOnly attribute 87

Chapter 10. Installation and configuration programs log information 89

Chapter 11. Post installation tasks . . . 91

Installing help locally	91
Installing help	91
IBM Knowledge Center configuration	92
Help components	93
Maximo Asset Management documentation library	94
Configuring initial data	96
Synchronizing users and groups	99
Adding sample data to the Maximo Asset Management database post configuration	99

Chapter 12. Maintaining EAR files . . 103

Building EAR files.	103
Manually deploying Work Center WAR files	104
Manually uninstalling applications from WebSphere Application Server Network Deployment	104
Manually installing applications in WebSphere Application Server Network Deployment	104

Chapter 13. Command line configuration 107

Configuration parameter validation	107
Input properties files	108
Command line interface parameters	109
Command line configuration program actions	116
action updateDatabaseConfiguration.	117

action validateDatabaseConfiguration	117
action validateAndUpdateDatabaseConfiguration	117
action deployDatabaseConfiguration.	118
action removeDatabaseConfiguration	118
action enableDB2TextSearch	118
action updateJ2eeConfiguration	118
action validateJ2eeConfiguration	119
action validateAndUpdateJ2eeConfiguration	119
action deployJ2eeConfiguration	119
action removeJ2EEConfiguration	120
action deployConfiguration.	120
action removeConfiguration	120
action reapplyAppServerTuning	120
action enableAppSecurity	120
action disableAppSecurity	121
action updateApplication	121
action addLanguages	121
action configureProducts	122
action deployMiddlewareConfiguration	122
action upgrade75Configuration	123
action updateApplicationDBLite	123
action configureProductsDBLite	124
Configuration program properties	124

Chapter 14. Backup and restoration 147

Backing up the administrative workstation	147
Restoring the administrative workstation	148

Chapter 15. Uninstalling the product 149

Remove Maximo Asset Management configuration	149
Removing WebSphere Application Server Network Deployment configuration	150
Uninstalling Maximo Asset Management and middleware	150

Notices 153

Trademarks	155
Terms and conditions for product documentation	155
IBM Online Privacy Statement.	156

Index 157

Chapter 1. Preparing for installation

These topics provide information about product media, preinstallation considerations, overview of the installation procedure, and instructions on using the Maximo® Asset Management launchpad.

Use the planning information to familiarize yourself with the overall process of a Maximo Asset Management deployment before you use this information to conduct the installation.

Software installation images

You access the IBM® Maximo Asset Management product software from IBM Passport Advantage.

The installation images that you download from Passport Advantage can comprise multiple downloadable files. Download all files in the package to a single directory and extract the files for execution.

For instructions and a full list of installation images, see the IBM Maximo Asset Management 7.6.1 Download Document (<http://www.ibm.com/support/docview.wss?uid=swg24044945>).

Installation program overview

You use the IBM Installation Manager to install Maximo Asset Management, IBM WebSphere® Application Server, and IBM DB2®.

You must run the installation program on the target system to install the component. For example, to install IBM WebSphere Application Server, you start the installation program locally on the system that is designated as the IBM WebSphere Application Server server.

Use the **Check for Other Versions, Fixes, and Extensions** button to search for fixes, updates, and extensions for the packages listed. The installation program downloads the latest version of the packages listed from IBM Fix Central.

Configuration program overview

You use the Maximo Asset Management configuration program to configure Maximo Asset Management and associated middleware.

The Maximo Asset Management configuration program is used to perform the following configuration tasks.

- Prepare IBM WebSphere Application Server for configuration of your product
- Configure a new Maximo Asset Management deployment
- Update database access credentials
- Change the Maximo Asset Management security model
- Change the database server host
- Update IBM WebSphere Application Server access credentials
- Change IBM WebSphere Application Server host

- Update database and build and deploy application EAR files
- Remove IBM WebSphere Application Server configuration
- Remove Maximo Asset Management configuration

The Maximo Asset Management configuration program records configuration choices that you make about your Maximo Asset Management deployment and then deploys Maximo Asset Management based on the information that you entered.

Information that you enter for the Maximo Asset Management configuration program is stored in the `maximo.properties` and `install.properties` files. Some of this information is also written to the Maximo database. These values are displayed in the panel fields of the Maximo Asset Management configuration program during an upgrade or fix pack application.

The Maximo Asset Management configuration program validates the values that you enter in configuration item fields. Some configuration item fields are validated as a pair, for example, user name and password fields.

In most cases, you can run the configuration program locally or remotely. You are required to run the configuration program locally on the IBM WebSphere Application Server server when you are preparing it for Maximo Asset Management configuration.

If you choose not to have the Maximo Asset Management configuration program automatically configure middleware, you must configure that piece of middleware manually before the configuration of Maximo Asset Management.

Note: If you are using a directory server to secure Maximo Asset Management, be aware of the product-specific syntax rules for using special characters in LDAP strings that you enter. In most cases, special characters must be preceded by an escape character to make them readable by the directory server.

Many directory server products consider a blank space to be a special character in an LDAP string. If you enter an LDAP string with an unescaped blank character at the end of a field value, you encounter Maximo Asset Management errors.

For more information about special character usage in LDAP strings, see the product documentation for your directory server.

Chapter 2. Automatically configuring middleware during deployment

Use the Maximo Asset Management installation and configuration programs to install and automatically configure a Maximo Asset Management deployment within your enterprise.

About this task

This information provides a high-level overview or road map of tasks you need to complete in order to deploy Maximo Asset Management with automatic middleware configuration.

In this scenario, you use the Maximo Asset Management installation and configuration programs to install and automatically configure new instances of the following components:

- Db2
- WebSphere Application Server Network Deployment
- Maximo Asset Management

You use the Maximo Asset Management installation program to install Maximo Asset Management and the middleware you want to use in your deployment. You then use the Maximo Asset Management configuration program to configure both middleware and Maximo Asset Management.

You can use the Maximo Asset Management installation program to install Db2. You then use the Maximo Asset Management configuration program to automatically configure it.




Figure 1. Deploying Maximo Asset Management using automatic middleware configuration

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment enables the Maximo Asset Management configuration program to automatically create users and groups in the directory. Users and groups must be created in the directory if you plan to use a directory server for Maximo Asset Management authentication and authorization. If you plan to use Maximo Asset Management application security for authentication and authorization, you do not need configure SSL for a directory server.

About this task

To enable the configuration program to automatically create users and groups within Microsoft Active Directory, you must configure SSL communication between

Microsoft Active Directory and WebSphere Application Server Network Deployment. This procedure is only required if you choose to allow the configuration program to automatically configure WebSphere Application Server Network Deployment. You also want the configuration program to automatically create users in Microsoft Active Directory.

You must enable SSL for Microsoft Active Directory, generate a certificate, and then add that certificate to WebSphere Application Server Network Deployment.

Changing the name or domain of the certificate authority at any point invalidates certificates previously issued from that authority.

Ensure that you have host name resolution setup properly in your environment. Communication failures occur if the system hosting Microsoft Active Directory cannot resolve host names for systems that have been issued certificates.

Installing Db2 v11.1 using the Maximo Asset Management version 7.6.1 installation program

Use the Maximo Asset Management version 7.6.1 installation program to install Db2 v11.1.

Procedure

1. Log in to the target system as a user with administrative authority. If you are running the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Run the Installation Manager from the following directory:

Option	Description
Windows	Start > All Programs > IBM Installation Manager > IBM Installation Manager
UNIX	In the /opt/IBM/InstallationManager/eclipse directory, run the IBMIM command.

- a. Select a language for the installation and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the Install IBM Maximo Asset Management panel, select **IBM Db2 v11.1** and then click **Install**.
3. In the package selection panel, click **Next**.
 4. In the package prerequisite validation panel, review the results of the prerequisite check and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.
 5. In the license agreement panel, review the license information for each package being installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.
 6. In the Installation Manager installation location panel, specify path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.

7. In the package installation location panel, select a package group, specify the path information for its installation directory, and then click **Next**.
8. In the package features panel, leave all default options checked, and then click **Next**.
9. In the package configuration panel, specify configuration information for Db2 v11.1, and then click **Next**.
10. In the package summary panel, review the information for the planned installation, and then click **Install**.

Installing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management version 7.6.1 Installation Manager

You can use the IBM Launchpad program to install WebSphere Application Server Network Deployment v9.0.0.7.

Procedure

1. Log in to the target system as a user with administrative authority. If you are running the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Start the Maximo Asset Management launchpad.

Option	Description
Windows	<code>launchpad64.exe</code>
Linux or UNIX	<code>./launchpad.sh</code>

- a. Select a language for the installation and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the Install IBM Maximo Asset Management panel, select **IBM WebSphere Application Server Network Deployment v9.0.0.7** and then click **Install**. During the installation of WebSphere Application Server Network Deployment, install Java v8. When you install Java v8, the configuration program configures IBM Maximo Asset Management to use Java v8.
3. In the package selection panel, click **Next**.
4. In the package prerequisite validation panel, review the results of the prerequisite check, and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.
5. In the license agreement panel, review the license information for each package that is to be installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.
6. In the Installation Manager installation location panel, specify the path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.

7. In the package installation location panel, select a package group, specify path information for its installation directory. Repeat this process for each package group that is listed and then click **Next**.
8. In the package translations panel, specify language support for WebSphere Application Server Network Deployment, and then click **Next**.
9. In the package features panel, leave all default options selected, and then click **Next**.
10. In the package configuration panel, specify configuration information for IBM HTTP Server, and then click **Next**.
11. In the package summary panel, review the information for the planned installation, and then click **Install**.
12. After the installation is complete, select the option to start the Maximo Asset Management version 7.6.1 configuration program, and then click **Finish**.

What to do next

Use the Maximo Asset Management version 7.6.1 configuration program to prepare WebSphere Application Server Network Deployment for Maximo Asset Management version 7.6.1 configuration.

Preparing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management configuration program

Use the Maximo Asset Management version 7.6.1 configuration program to prepare WebSphere Application Server Network Deployment v9.0.0.7 for Maximo Asset Management configuration.

Procedure

1. If the Maximo Asset Management launchpad isn't working with your web browser, navigate to the installation directory for the **IBM Tivoli's Process Automation Suite configuration program** for WebSphere Application Server (whose default is /opt/IBM/SMP on Linux/UNIX or C:\IBM\SMP on windows). Navigate to the ConfigTool directory and start ConfigUI.exe on Windows or ConfigUI for UNIX.
2. In the IBM Maximo Asset Management version 7.6.1 configuration operations page, click **Configure WebSphere Application Server**.
3. In the Configure Application Server Profiles pane, specify information to use to create the WebSphere Application Server Network Deployment deployment manager and application server profiles.
4. Optional: In the Configure Application Server Advanced Options pane, specify additional configuration information, if required.
5. If you chose to use a directory server for WebSphere Application Server Network Deployment administrative security, specify information about the directory server host, credentials, and directory structure from the Configure Administrative Security pane.
6. In the Apply Deployment Operations pane, select all deployment operation options, and then click **Finish**.

Results

WebSphere Application Server Network Deployment v9.0.0.7 is ready for Maximo Asset Management.

Running the Maximo Asset Management 7.6.1 installation program

Use the Maximo Asset Management version 7.6.1 installation program to install Maximo Asset Management version 7.6.1.

Before you begin

Maximo Asset Management version 7.6.1 must be installed in a separate location on the administration workstation to any existing Maximo Asset Management versions.

About this task

In order to install Maximo Asset Management version 7.6.1, run the Maximo Asset Management version 7.6.1 installation program on the Maximo Asset Management administrative system.

Procedure

1. Log in to the Maximo Asset Management administrative workstation. If you run the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Start the Maximo Asset Management launchpad.

Option	Description
Windows	<code>launchpad64.exe</code>
Linux or UNIX	<code>./launchpad.sh</code>

- a. Select a language for the installation session and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the **Install IBM Maximo Asset Management** panel, select **IBM Maximo Asset Management v7.6.1** and then click **Install**.
3. In the package selection panel, click **Next**.
 4. In the package prerequisite validation panel, review the results of the prerequisite check, and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.
 5. In the license agreement panel, review the license information for each package being installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.
 6. In the Installation Manager installation location panel, specify path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.
 7. In the package installation location panel, select the IBM Tivoli's process automation suite package group, specify the path information for the Maximo Asset Management version 7.6.1 installation directory, and then click **Next**.
 8. In the package summary panel, review the information for the planned installation, and then click **Install**. If you install in a non-English environment, you might notice the environment summary is listed as English. You configure

supported languages for Maximo Asset Management later with the Maximo Asset Management configuration program.

9. After the installation is complete, select the option to start the Maximo Asset Management version 7.6.1 configuration program, and then click **Finish**. The Maximo Asset Management version 7.6.1 installation program exits and the Maximo Asset Management version 7.6.1 configuration program is started automatically.

What to do next

Use the Maximo Asset Management version 7.6.1 configuration program to configure Maximo Asset Management version 7.6.1.

Configuring Maximo Asset Management version 7.6.1 using the Maximo Asset Management version 7.6.1 configuration program

Use the Maximo Asset Management version 7.6.1 configuration program to configure Maximo Asset Management version 7.6.1.

Procedure

1. Start the configuration program:

Option	Description
Windows 8 and above	C:\IBM\SMP\ConfigTool\ConfigUI.exe or <i>InstallLocation</i> \ConfigTool\ConfigUI.exe
UNIX	<i>InstallLocation</i> /ConfigTool/ConfigUI. For example, /opt/IBM/SMP/ConfigTool/ConfigUI.

2. In the **Deployment Operations** pane, select **Configure a new Deployment** or **Configure a new Administrative Workstation to point to an existing Maximo Asset Management deployment** depending on your environment.
3. To complete the configuration, follow the on-screen instructions.

Results

Maximo Asset Management version 7.6.1 is installed and configured to use WebSphere Application Server Network Deployment .

Creating the NOTF JMS queue

You must create a JMS queue NOTF for notifications.

About this task

You must create a JMS queue called NOTF to enable notifications. If you do not use the Maximo Asset Management configuration program to automatically configure WebSphere Application Server Network Deployment, you must create this queue manually.

For Maximo Asset Management multitenancy environments, the system provider must create the NOTF queue manually to enable notifications for each tenant. These queues cannot be created automatically by using Maximo Asset Management installation and configuration programs.

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the **Scope** drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the default messaging provider is selected and then click **OK**.
5. Enter the following information, and then click **OK**.

Name NOTF.

This value must contain only uppercase letters.

JNDI name

jms/maximo/int/queues/notf

Bus name

intjmsbus.

Queue name

CQINBD.

6. Click **OK** and then click **Save**.

Creating the NOTFERR JMS queue

After creating the Error Queue Bus Destination, you create the NOTFERR Error queue for notification error handling.

About this task

You must create a JMS queue called NOTFERR to enable notification error handling. If you do not use the Maximo Asset Management configuration program to automatically configure WebSphere Application Server Network Deployment, you must create this queue manually.

For Maximo Asset Management multitenancy environments, the system provider must create the NOTF queue manually to enable notifications for each tenant. These queues cannot be created automatically by using Maximo Asset Management installation and configuration programs.

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the **Scope** drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the default messaging provider is selected and then click **OK**.
5. Enter the following information, and then click **OK**.

Name Enter NOTFERR.

This value must contain only uppercase letters.

JNDI name

Enter jms/maximo/int/queues/notferr

Bus name

Select **intjmsbus**.

Queue name

Select **CQINERRBD**.

6. Click **OK** and then click **Save**.

Chapter 3. Automatically configuring existing middleware during deployment

Use the Maximo Asset Management configuration program to automatically configure existing middleware within your enterprise for use with Maximo Asset Management

About this task

This information provides a high-level overview or roadmap of tasks you must complete to deploy Maximo Asset Management automatically. You use middleware that is already established in your enterprise.




Figure 2. Deploying Maximo Asset Management reusing existing middleware

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment enables the Maximo Asset Management configuration program to automatically create users and groups in the directory. Users and groups must be created in the directory if you plan to use a directory server for Maximo Asset Management authentication and authorization. If you plan to use Maximo Asset Management application security for authentication and authorization, you do not need configure SSL for a directory server.

About this task

To enable the configuration program to automatically create users and groups within Microsoft Active Directory, you must configure SSL communication between Microsoft Active Directory and WebSphere Application Server Network Deployment. This procedure is only required if you choose to allow the configuration program to automatically configure WebSphere Application Server Network Deployment. You also want the configuration program to automatically create users in Microsoft Active Directory.

You must enable SSL for Microsoft Active Directory, generate a certificate, and then add that certificate to WebSphere Application Server Network Deployment.

Changing the name or domain of the certificate authority at any point invalidates certificates previously issued from that authority.

Ensure that you have host name resolution setup properly in your environment. Communication failures occur if the system hosting Microsoft Active Directory cannot resolve host names for systems that have been issued certificates.

Preparing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management configuration program

Use the Maximo Asset Management version 7.6.1 configuration program to prepare WebSphere Application Server Network Deployment v9.0.0.7 for Maximo Asset Management configuration.

Procedure

1. If the Maximo Asset Management launchpad isn't working with your web browser, navigate to the installation directory for the **IBM Tivoli's Process Automation Suite configuration program** for WebSphere Application Server (whose default is /opt/IBM/SMP on Linux/UNIX or C:\IBM\SMP on windows). Navigate to the ConfigTool directory and start ConfigUI.exe on Windows or ConfigUI for UNIX.
2. In the IBM Maximo Asset Management version 7.6.1 configuration operations page, click **Configure WebSphere Application Server**.
3. In the Configure Application Server Profiles pane, specify information to use to create the WebSphere Application Server Network Deployment deployment manager and application server profiles.
4. Optional: In the Configure Application Server Advanced Options pane, specify additional configuration information, if required.

5. If you chose to use a directory server for WebSphere Application Server Network Deployment administrative security, specify information about the directory server host, credentials, and directory structure from the Configure Administrative Security pane.
6. In the Apply Deployment Operations pane, select all deployment operation options, and then click **Finish**.

Results

WebSphere Application Server Network Deployment v9.0.0.7 is ready for Maximo Asset Management.

Running the Maximo Asset Management 7.6.1 installation program

Use the Maximo Asset Management version 7.6.1 installation program to install Maximo Asset Management version 7.6.1.

Before you begin

Maximo Asset Management version 7.6.1 must be installed in a separate location on the administration workstation to any existing Maximo Asset Management versions.

About this task

In order to install Maximo Asset Management version 7.6.1, run the Maximo Asset Management version 7.6.1 installation program on the Maximo Asset Management administrative system.

Procedure

1. Log in to the Maximo Asset Management administrative workstation. If you run the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Start the Maximo Asset Management launchpad.

Option	Description
Windows	launchpad64.exe
Linux or UNIX	./launchpad.sh

- a. Select a language for the installation session and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the **Install IBM Maximo Asset Management** panel, select **IBM Maximo Asset Management v7.6.1** and then click **Install**.
3. In the package selection panel, click **Next**.
4. In the package prerequisite validation panel, review the results of the prerequisite check, and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.
5. In the license agreement panel, review the license information for each package being installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.

6. In the Installation Manager installation location panel, specify path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.
7. In the package installation location panel, select the IBM Tivoli's process automation suite package group, specify the path information for the Maximo Asset Management version 7.6.1 installation directory, and then click **Next**.
8. In the package summary panel, review the information for the planned installation, and then click **Install**. If you install in a non-English environment, you might notice the environment summary is listed as English. You configure supported languages for Maximo Asset Management later with the Maximo Asset Management configuration program.
9. After the installation is complete, select the option to start the Maximo Asset Management version 7.6.1 configuration program, and then click **Finish**. The Maximo Asset Management version 7.6.1 installation program exits and the Maximo Asset Management version 7.6.1 configuration program is started automatically.

What to do next

Use the Maximo Asset Management version 7.6.1 configuration program to configure Maximo Asset Management version 7.6.1.

Configuring Maximo Asset Management version 7.6.1 using the Maximo Asset Management version 7.6.1 configuration program

Use the Maximo Asset Management version 7.6.1 configuration program to configure Maximo Asset Management version 7.6.1.

Procedure

1. Start the configuration program:

Option	Description
Windows 8 and above	C:\IBM\SMP\ConfigTool\ConfigUI.exe or <i>InstallLocation</i> \ConfigTool\ConfigUI.exe
UNIX	<i>InstallLocation</i> /ConfigTool/ConfigUI. For example, /opt/IBM/SMP/ConfigTool/ConfigUI.

2. In the **Deployment Operations** pane, select **Configure a new Deployment** or **Configure a new Administrative Workstation to point to an existing Maximo Asset Management deployment** depending on your environment.
3. To complete the configuration, follow the on-screen instructions.

Results

Maximo Asset Management version 7.6.1 is installed and configured to use WebSphere Application Server Network Deployment .

Creating the NOTF JMS queue

You must create a JMS queue NOTF for notifications.

About this task

You must create a JMS queue called NOTF to enable notifications. If you do not use the Maximo Asset Management configuration program to automatically configure WebSphere Application Server Network Deployment, you must create this queue manually.

For Maximo Asset Management multitenancy environments, the system provider must create the NOTF queue manually to enable notifications for each tenant. These queues cannot be created automatically by using Maximo Asset Management installation and configuration programs.

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the **Scope** drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the default messaging provider is selected and then click **OK**.
5. Enter the following information, and then click **OK**.

Name NOTF.

This value must contain only uppercase letters.

JNDI name

jms/maximo/int/queues/notf

Bus name

intjmsbus.

Queue name

CQINBD.

6. Click **OK** and then click **Save**.

Creating the NOTFERR JMS queue

After creating the Error Queue Bus Destination, you create the NOTFERR Error queue for notification error handling.

About this task

You must create a JMS queue called NOTFERR to enable notification error handling. If you do not use the Maximo Asset Management configuration program to automatically configure WebSphere Application Server Network Deployment, you must create this queue manually.

For Maximo Asset Management multitenancy environments, the system provider must create the NOTF queue manually to enable notifications for each tenant. These queues cannot be created automatically by using Maximo Asset Management installation and configuration programs.

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the **Scope** drop-down list, select **Cell=ctgCell01**.
3. Click **New**.

4. Verify that the default messaging provider is selected and then click **OK**.
5. Enter the following information, and then click **OK**.

Name Enter NOTFERR.

This value must contain only uppercase letters.

JNDI name

Enter `jms/maximo/int/queues/notferr`

Bus name

Select **intjmsbus**.

Queue name

Select **CQINERRBD**.

6. Click **OK** and then click **Save**.

Chapter 4. Manually configuring existing middleware during deployment

You can deploy Maximo Asset Management by reusing existing middleware servers and manually configuring them to work with Maximo Asset Management.

This information provides a high-level overview or road map of tasks you need to complete in order to deploy Maximo Asset Management automatically, using middleware already established in your enterprise.

In this scenario, you manually configure existing middleware resources before running the Maximo Asset Management configuration program.




Figure 3. Deploying Maximo Asset Management with manual middleware configuration

Maximo Asset Management installation with manual middleware configuration

Manually configured installations involve configuring middleware components, the database server, the directory server, and the J2EE server, to work with Maximo Asset Management before you use the Maximo Asset Management installation and configuration programs.

You can automatically configure one or more Maximo Asset Management middleware components with the Maximo Asset Management configuration program. Alternatively, you can manually configure middleware servers to work with Maximo Asset Management before you run the Maximo Asset Management installation and configuration programs..

Before you begin, ensure that the following prerequisite conditions are met:

- You designate a Windows or UNIX server to start the Maximo Asset Management configuration program.
- For WebSphere Application Server Network Deployment, ensure that the Cell and all related nodes are active.

You must complete the manual configuration of each middleware server before you use the Maximo Asset Management configuration program to configure Maximo Asset Management to work with the servers.

Ensure that the middleware you intend to use with Maximo Asset Management is supported.

Manual configuration of the database

You can manually configure the database server that is used with Maximo Asset Management. You must manually configure the database server before you use the Maximo Asset Management installation and configuration programs.

For Db2 on UNIX and Linux, a minimum of 8 gigabytes (binary) free of space is required for Db2 table spaces. This space must be available to the database instance home directory (/home/ctginst1).

For Db2 on Windows, ensure that you have a minimum of 8 gigabytes of free space in the Db2 installation directory.

Manually configuring Db2 v11.1

Manually configuring Db2 v11.1 servers for use by Maximo Asset Management.

Before you begin

If you plan to support full-text search, ensure that it is enabled in Db2.

About this task

To configure an existing Db2 v11.1 server for use with Maximo Asset Management, complete the following steps before you start the Maximo Asset Management installation and configuration programs:

Procedure

1. Log in to the system as a user that has administrative permissions on the system.
2. Create system users if they do not exist on the system.
 - Windows
 - db2admin
 - maximo
 - Linux or UNIX
 - db2admin

- maximo
- ctgfenc1
- ctginst1

The ctginst1 user ID must be assigned to db2iadm1 as its primary group.

3. Open a console window and set up the Db2 environment:

- Windows

db2cmd

- Linux or UNIX

Ensure that the /opt/ibm/db2/V11.1/bin, /opt/ibm/db2/v11.1/instance, and /opt/ibm/db2/V11.1/adm directories are added to your PATH.

4. Create the Db2 instance:

- Windows

```
db2icrt -s ese -u db2admin,myPassword -r 50005,50005 ctginst1
set db2instance=ctginst1
db2start
db2 update dbm config using SVCENAME 50005 DEFERRED
db2stop
db2set DB2COMM=tcpip
db2start
```

- Linux orUNIX

```
db2icrt -s ese -u ctgfenc1 -p 50005 ctginst1
./home/ctginst1/sql/lib/db2/profile
db2start
db2 update dbm config using SVCENAME 50005 DEFERRED
db2stop
db2set DB2COMM=tcpip
db2start
```

5. Create the database.

```
db2 create db 'maxdb76' ALIAS 'maxdb76' using codeset UTF-8 territory US pagesize 32 K
db2 connect to 'maxdb76'
db2 GRANT DBADM ON DATABASE TO USER db2admin (windows only)
db2 GRANT SECADM ON DATABASE TO USER db2admin (windows only)
db2 connect reset
```

6. Configure the database.

```
db2 update db cfg for maxdb76 using SELF_TUNING_MEM ON
db2 update db cfg for maxdb76 using APPGROUP_MEM_SZ 16384 DEFERRED
db2 update db cfg for maxdb76 using APPLHEAPSZ 2048 AUTOMATIC DEFERRED
db2 update db cfg for maxdb76 using AUTO_MAINT ON DEFERRED
db2 update db cfg for maxdb76 using AUTO_TBL_MAINT ON DEFERRED
db2 update db cfg for maxdb76 using AUTO_RUNSTATS ON DEFERRED
db2 update db cfg for maxdb76 using AUTO_REORG ON DEFERRED
db2 update db cfg for maxdb76 using AUTO_DB_BACKUP ON DEFERRED
db2 update db cfg for maxdb76 using CATALOGCACHE_SZ 800 DEFERRED
db2 update db cfg for maxdb76 using CHNGPGS_THRESH 40 DEFERRED
db2 update db cfg for maxdb76 using DBHEAP AUTOMATIC
db2 update db cfg for maxdb76 using LOCKLIST AUTOMATIC DEFERRED
db2 update db cfg for maxdb76 using LOGBUFSZ 1024 DEFERRED
db2 update db cfg for maxdb76 using LOCKTIMEOUT 300 DEFERRED
db2 update db cfg for maxdb76 using LOGPRIMARY 20 DEFERRED
db2 update db cfg for maxdb76 using LOGSECOND 100 DEFERRED
db2 update db cfg for maxdb76 using LOGFILSIZ 8192 DEFERRED
db2 update db cfg for maxdb76 using SOFTMAX 1000 DEFERRED
db2 update db cfg for maxdb76 using MAXFILOP 32768 DEFERRED #32-bit Windows
db2 update db cfg for maxdb76 using MAXFILOP 65335 DEFERRED #64-bit Windows
db2 update db cfg for maxdb76 using MAXFILOP 30720 DEFERRED #32-bit UNIX
db2 update db cfg for maxdb76 using MAXFILOP 61440 DEFERRED #64-bit UNIX
db2 update db cfg for maxdb76 using PCKCACHESZ AUTOMATIC DEFERRED
db2 update db cfg for maxdb76 using STAT_HEAP_SZ AUTOMATIC DEFERRED
db2 update db cfg for maxdb76 using STMTHAP AUTOMATIC DEFERRED
db2 update db cfg for maxdb76 using UTIL_HEAP_SZ 10000 DEFERRED
db2 update db cfg for maxdb76 using DATABASE_MEMORY AUTOMATIC DEFERRED
db2 update db cfg for maxdb76 using AUTO_STMT_STATS OFF DEFERRED
db2 update db cfg for maxdb76 using STMT_CONC LITERALS DEFERRED
db2 update alert cfg for database on maxdb76 using db.db_backup_req SET THRESHOLDSCHECKED YES
db2 update alert cfg for database on maxdb76 using db.tb_reorg_req SET THRESHOLDSCHECKED YES
db2 update alert cfg for database on maxdb76 using db.tb_runstats_req SET THRESHOLDSCHECKED YES
db2 update dbm cfg using PRIV_MEM_THRESH 32767 DEFERRED
db2 update dbm cfg using KEEPFENCED NO DEFERRED
db2 update dbm cfg using NUMDB 2 DEFERRED
db2 update dbm cfg using RQRIOBLK 65535 DEFERRED
db2 update dbm cfg using HEALTH_MON OFF DEFERRED
#
# Windows: AGENT_STACK_SZ 1000
# Unix : AGENT_STACK_SZ 1000
#
db2 update dbm cfg using AGENT_STACK_SZ 1000 DEFERRED
db2 update dbm cfg using MON_HEAP_SZ AUTOMATIC DEFERRED
db2set DB2_SKIPINSERTED=ON
db2set DB2_INLIST_TO_NLJN=YES
db2set DB2_MINIMIZE_LISTPREFETCH=Y
db2set DB2_EVALUNCOMMITTED=YES
db2set DB2_FMP_COMM_HEAPSZ=65536
db2set DB2_SKIPDELETED=ON
db2set DB2_USE_ALTERNATE_PAGE_CLEANING=ON
```

7. For Linux orUNIX, log into the system as the ctginst1 user, and then restart the Db2 command-line environment.

- ```

su - ctginst1
db2

```
8. Restart Db2.

```

db2stop force
db2start

```
  9. Reconnect to the database.

```

db2 connect to 'maxdb76'

```
  10. Create a buffer pool.

```

db2 CREATE BUFFERPOOL MAXBUFFERPOOL IMMEDIATE SIZE 4096 AUTOMATIC PAGESIZE 32 K

```
  11. Create table spaces.

```

db2 CREATE REGULAR TABLESPACE MAXDATA PAGESIZE 32 K MANAGED BY AUTOMATIC STORAGE INITIALSIZE 5000 M BUFFERPOOL MAXBUFFERPOOL
db2 CREATE TEMPORARY TABLESPACE MAXTEMP PAGESIZE 32 K MANAGED BY AUTOMATIC STORAGE BUFFERPOOL MAXBUFFERPOOL
db2 CREATE REGULAR TABLESPACE MAXINDEX PAGESIZE 32 K MANAGED BY AUTOMATIC STORAGE INITIALSIZE 5000 M BUFFERPOOL MAXBUFFERPOOL
db2 GRANT USE OF TABLESPACE MAXDATA TO USER MAXIMO

```
  12. Create Schema

```

db2 create schema maximo authorization maximo

```
  13. Grant authority to maximo.

```

db2 GRANT DBADM,CREATETAB,BINDADD,CONNECT,CREATE_NOT_FENCED_ROUTINE,IMPLICIT_SCHEMA,
LOAD,CREATE_EXTERNAL_ROUTINE,QUIESCE_CONNECT,SECADM ON DATABASE TO USER MAXIMO

db2 GRANT USE OF TABLESPACE MAXDATA TO USER MAXIMO

db2 GRANT CREATEIN,DROPIN,ALTERIN ON SCHEMA MAXIMO TO USER MAXIMO

```
  14. Break the database connection.

```

db2 connect reset

```
  15. Exit the Db2 command-line environment
  16. Install the appropriate fix pack that is indicated in the prerequisites topic in the chapter that describes how to prepare for the installation. Ensure that you review and complete all the installation and postinstallation tasks that are contained within the fix pack readme file. Failure to do so can potentially cause the Maximo Asset Management installation to fail.

## Manually configuring Microsoft SQL Server 2012

You can manually configure Microsoft SQL Server for use with Maximo Asset Management.

### Before you begin

Because Microsoft SQL Server does not support UTF-8, multilingual support is limited. You can support multiple languages on one database instance only if they share the same character set. For example, a database instance could support English, French, and Portuguese because they use the same character set. A database instance could not support both Portuguese and Chinese because they have different character sets.

Microsoft SQL Server Database Collation settings must be set to the following options:

- Dictionary order
- Case-insensitive
- For use with 1252 Character set

### About this task

To configure an existing Microsoft SQL Server for use with Maximo Asset Management, complete the following steps before you start the Maximo Asset Management installation and configuration programs:

## Procedure

### 1. Configure the listener port.

If The default instance of the Microsoft SQL Server Database Engine listens on TCP port 1433. Named instances of the Microsoft SQL Server Database Engine and Microsoft SQL Server Compact Edition are configured for dynamic ports, which means they select any available port when the service starts. When you connect to a named instance across a firewall, configure the Database Engine to listen on a specific port, to open this port in the firewall.

- a. Open **Programs > Microsoft SQL Server 2012 > Configuration Tools > SQL Server Configuration Manager**
- b. From the Microsoft SQL Server Configuration Manager navigation pane, expand **SQL Server Network Configuration > Protocols for <instance name>**, and then double-click **TCP/IP**.
- c. In the TCP/IP Properties dialog box, click the **IP Addresses** tab.
- d. For each IP address listed, ensure that the **TCP Dynamic Ports** field is blank. If the **TCP Dynamic Ports** field contains a value of 0, that IP address is using dynamic ports. Since Maximo Asset Management requires Microsoft SQL Server to listen on a static port, this field must be blank.
- e. For each IP address listed, enter 1433 for the **TCP Port** field.
- f. Click **OK**.
- g. From the SQL Server Configuration Manager navigation pane, click **SQL Server Services**.
- h. Right-click **SQL Server (<instance name>)** and then click **Restart**, to stop, and restart Microsoft SQL Server.
- i. Verify the Microsoft SQL Server instance is running, and then close SQL Server Configuration Manager.

### 2. Verify that you enabled the Full-text Search setting during the installation of Microsoft SQL Server 2012. To determine if Full-text Search is installed on your existing Microsoft SQL Server database, complete the following steps:

- a. Open SQL Server Management Studio, select **SQL Server Authentication** as the authentication type, and enter the credentials for the **sa** user ID, and then click **Connect**.
- b. Click **New Query**.
- c. Type the following command and then click **Execute**:

```
select FULLTEXTSERVICEPROPERTY ('IsFulltextInstalled')
```

If you did not install Full-text Search (the resulting value is zero), you must do so now. To install Full-text Search, insert the Microsoft SQL Server 2012 product media into the system and start the installation wizard. Navigate through the wizard and enable the Full-Text Search option that is on the Custom portion of the Setup Type dialog box. To finish the installation process, restart the server.

### 3. Create a Microsoft SQL Server database.

- a. Open SQL Server Management Studio (**Start > Programs > Microsoft SQL Server 2012 > SQL Server Management Studio**)
- b. Right-click the databases folder from the navigation tree, and select **New Database**.
- c. In the database name entry field, specify a unique database name. For example, enter **maxdb76**
- d. For the **maxdb76** Logical Name, change the Initial Size (MB) attribute to 500 (MB), and also set the value of the **Autogrowth / Maxsize** field to **By 1 MB, Unlimited**.

- e. If you prefer, modify the log settings to accommodate your production environment.
  - f. Click **OK**.
4. Create the Maximo User for Microsoft SQL Server.
    - a. Open Microsoft SQL Server Management Studio (**Start > Programs > Microsoft SQL Server 2012 > SQL Server Management Studio**)
    - b. From the SQL Server Configuration Manager navigation pane, click **Databases**.
    - c. Right-click the **maxdb76** database and select **New Query**.
    - d. Enter the following script to create the Maximo database user MAXIMO with a password that adheres to the password policy of the system.
 

```
sp_addlogin MAXIMO,password
go
```

This value is case-sensitive.
    - e. Click **Execute**.
    - f. Enter the following script to change the database owner to maximo.
 

```
sp_changedbowner MAXIMO
go
```
    - g. Click **Execute**.

### What to do next

If you add logical names to the database and set their file group to a value other than PRIMARY, complete these steps after you set up the database and create the Maximo user:

1. Add the following property to the *install\_home\etc\install.properties* file:
 

```
Database.SQL.DataFilegroupName=your_logical_name
```
2. Run the configuration tool to complete the deployment.

Complete these additional steps only if you added logical names to the database and set their file group to a value other than PRIMARY.

## Manual configuration of the directory server

You can manually configure a directory server for Maximo Asset Management to manage authentication and authorization.

There are several methods to secure Maximo Asset Management. If you want to use a directory server to secure Maximo Asset Management, you must complete the manual configuration of the directory server before you use the Maximo Asset Management installation and configuration programs.

**Note:** The base dn, bind user, and other various node values that are listed are default values. These values are replaced with values applicable to existing LDAP hierarchies within your organization.

**Important:** When you enter LDAP values for Maximo Asset Management configuration panel fields, entries in LDIF files, or values you enter directly into a directory instance with directory server tools, be aware of the product-specific syntax rules for using special characters in an LDAP string. In most cases, special characters must be preceded by an escape character to make it readable by the

directory server. Failing to escape special characters that are contained in an LDAP string that is used with Maximo Asset Management results in Maximo Asset Management errors.

Many directory server products consider a blank space as a special character that is part of the LDAP string. If you mistakenly enter an LDAP string that contains a blank, at the end of a field value, for example, and you do not precede the blank character with an escape character, you encounter Maximo Asset Management errors that are difficult to troubleshoot.

For more information about special characters in LDAP strings, see the product documentation for your directory server.

## **Manually configuring IBM Security Directory Server**

Manually configure IBM Security Directory Server for use with Maximo Asset Management.

### **About this task**

If you choose the option to configure WebSphere Application Server Network Deployment automatically with the Maximo Asset Management configuration program, then you can create these users and groups automatically. If you do not want the Maximo Asset Management configuration program to configure WebSphere Application Server Network Deployment, you must create users manually.

To configure IBM Security Directory Server before you start the Maximo Asset Management installation and configuration programs, you must create an instance of IBM Security Directory Server.

**Note:** While you can technically share a Db2 instance between Maximo Asset Management and the one needed by IBM Security Directory Server, it might lead to problems. During the installation, the database instance is restarted, which might disrupt the availability of IBM Security Directory Server to your enterprise. If you are using the automated installation programs, separate instances are created for use by Maximo Asset Management and IBM Security Directory Server.

### **Procedure**

1. Using your preferred method, create a user on the system and assign it to the appropriate group.

#### **Windows**

Create the user db2admin and make it a member of the following groups:

- Windows Administrators
- DB2ADMNS
- DB2USERS

**UNIX** Create the user idscmdb and make it a member of the following groups:

- dasadm1
- idslsap
- dbsysadm

The root user must also be a member of the dasadm1, idslsap, and dbsysadm groups.

2. If the Instance Administration tool is not already started, ensure that you are logged in as an administrator on the system, and then start the tool

#### **Windows**

Select **Programs > IBM Tivoli Directory Server 6.3 > Instance Administration Tool**.

**UNIX** Type `/opt/IBM/ldap/V6.3/sbin/idsxinst` at the command line.

3. In the Instance Administration tool, click **Create an instance**.
4. In the Create a new instance window, click **Create a new directory server instance**, and then click **Next**.
5. From the Instance details window, enter values for the following fields, and then click **Next**.

#### **User name**

Select `idsccmdb` as the system user ID of the user who owns the instance. This name is also the name of the instance.

#### **Install location**

Enter the location where the instance files are stored.

#### **Encryption seed string**

Type a string of characters that are used as an encryption seed. This value must be a minimum of 12 characters.

#### **Instance description**

Enter a brief description of the instance.

6. In the Db2 instance details panel, enter `idsccmdb` as the value for the Db2 instance name field, and then click **Next**.
7. In the TCP/IP settings for multihomed hosts panel, select **Listen on all configured IP addresses**, and then click **Next**.
8. In the TCP/IP port settings panel, complete the following fields, and then click **Next**.

#### **Server port number**

Enter 389 as the contact port for the server.

#### **Server secure port number**

Enter 636 as the secure port for the server.

#### **Admin daemon port number**

Enter 3538 as the administration daemon port.

#### **Admin daemon secure port number**

Enter 3539 as the administration daemon secure port.

9. In the Option steps panel, leave the following options selected, and then click **Next**.

#### **Configure admin DN and password**

You want to configure the administrator DN and password for the instance now.

#### **Configure database**

You want to configure the database for the directory server now.

10. In the Configure administrator DN and password panel, complete the following fields, and then click **Next**.

#### **Administrator DN**

Enter `cn=root` for the administrator distinguished name.

### Administrator Password

Enter a password for the Administrator DN.

11. From the Configure database panel, complete the following fields, and then click **Next**.

### Database user name

Enter `idsccmdb` as the database user.

### Password

Enter the password for the `idsccmdb` user.

### Database name

Enter `idsccmdb` as the database to be used with this directory instance.

12. In the Database options panel, complete the following fields, and then click **Next**.

### Database install location

Type the location for the database.

### Windows

For Windows platforms, this value must be a drive letter.

**UNIX** For non-Windows systems, the location must be a directory name, such as `/home/ldapdb`.

Ensure that you have at least 80 MB of free hard disk space in the location you specify. More disk space must be available to accommodate growth as new entries are added to the directory.

### Character-set option

Leave the **Create a universal DB2 database (UTF-8/UCS-2)** option selected.

13. In the Verify settings panel, review the instance creation details that are provided, and then click **Finish** to create the `idsccmdb` instance.
14. Click **Close** to close the window and return to the main window of the Instance Administration tool.
15. Click **Close** to exit the Instance Administration tool.
16. Start the IBM Security Directory Server Configuration tool:

### Windows

Select **Programs > IBM Tivoli Directory Server 6.3 > Instance Administration Tool**.

**UNIX** Type `./opt/IBM/ldap/V6.3/sbin/idsxcfg` at the command line.

17. Select **Manage suffixes**.
18. In the Manage suffixes panel, type the following suffix, and then click **Add**.  
`o=IBM,c=US`
19. Click **OK**.
20. Create and save an LDIF file.  
Add the DN information, for example:
  - `ou=SWG,o=IBM,c=US`
  - `ou=users`

**Note:** `ou=SWG,o=IBM,c=US` in this example is an organization unit called SWG. SWG houses the OU=Users organization units to place the users that are created for Maximo Asset Management. `DC=IBM` and `DC=COM` would indicate a domain forest of `ibm.com`<sup>®</sup>. You can replace the example with the directory structure of your own organization.

Define the following users and their positions within the ou=users DN's you created. These users are defined in order for Virtual Member Manager to be used to secure Maximo Asset Management.

**Important:** Before you begin this procedure, create the following users in the root of your LDAP repository:

*Table 1. Base Maximo Asset Management users*

| User     |
|----------|
| wasadmin |
| maxadmin |
| mxintadm |
| maxreg   |

Here is an example of the default base LDIF data:

```
dn: o=ibm,c=us
objectClass: top
objectClass: organization
o: IBM

dn: ou=SWG, o=ibm,c=us
ou: SWG
objectClass: top
objectClass: organizationalUnit

dn: ou=users,ou=SWG, o=ibm,c=us
ou: users
objectClass: top
objectClass: organizationalUnit
dn: cn=wasadmin,ou=users,ou=SWG, o=ibm,c=us
uid: wasadmin
userpassword: wasadmin
objectclass: organizationalPerson
objectclass: inetOrgPerson
objectclass: person
objectclass: top
title: WebSphere Administrator
sn: wasadmin
cn: wasadmin
dn: uid=maxadmin,ou=users,ou=SWG, o=ibm,c=us
userPassword: maxadmin
uid: maxadmin
objectClass: inetorgperson
objectClass: top
objectClass: person
objectClass: organizationalPerson
sn: maxadmin
cn: maxadmin

dn: uid=mxintadm,ou=users,ou=SWG, o=ibm,c=us
userPassword: mxintadm
uid: mxintadm
objectClass: inetorgperson
objectClass: top
objectClass: person
objectClass: organizationalPerson
sn: mxintadm
cn: mxintadm

dn: uid=maxreg,ou=users,ou=SWG, o=ibm,c=us
userPassword: maxreg
```

```
uid: maxreg
objectClass: inetorgperson
objectClass: top
objectClass: person
objectClass: organizationalPerson
sn: maxreg
cn: maxreg
```

**Note:** If you create the LDIF file on Windows, ensure that you remove the ^M characters from the file before you use it.

**Note:** Before you can import an LDIF file on UNIX systems, you must run the dos2unix command to format the file.

21. In the IBM Security Directory Server Configuration tool, click **Import LDIF data**.
22. Click **Browse** to locate the LDIF file.
23. Click **Import**.
24. Close the IBM Security Directory Server Configuration tool and restart the server.

## Manually configuring Microsoft Active Directory version 2012

You can manually configure Microsoft Active Directory for use with Maximo Asset Management.

### Before you begin

Manually configure Microsoft Active Directory for authorization and authentication within Maximo Asset Management. If you choose the option to configure WebSphere Application Server Network Deployment automatically with the Maximo Asset Management configuration program, then you can create these users and groups automatically. If you do not want the Maximo Asset Management configuration program to configure WebSphere Application Server Network Deployment, you must create users manually. Creating users automatically requires SSL communication between Microsoft Active Directory and WebSphere Application Server Network Deployment.

**Important:** The users and passwords you create in the following steps must match this exact configuration for the deployment to succeed. It is sometimes necessary to temporarily alter the Microsoft Active Directory security policy to create these accounts in the required format. After installation, you can change these default passwords to conform to a stricter security policy.

### About this task

Before you start the Maximo Asset Management installation and configuration programs, configure Microsoft Active Directory. Complete the following steps

### Procedure

1. Add the Active Directory Domain Services role.
  - a. Start the Server Manager.
  - b. Click **Add roles and features**.
  - c. From the Before You Begin page, click **Next**.
  - d. For Installation Type, select **Role-based or feature-based installation**, and then click **Next**.

- e. Select the **Select a server from the server pool** option, and then choose your local server from the Server Pool list. Click **Next**
  - f. In the Roles list, select **Active Directory Domain Services**.
  - g. Click **Add Features**.
  - h. Click **Next**.
  - i. From the Select Features page , accept the defaults and click **Next**
  - j. On the confirmation page, click **Install**
  - k. Click **Close** when the installation is complete and then restart the server.
2. Promote the server to a Domain Controller.
    - a. Start the Server Manager.
    - b. Click **AD DS** in the dashboard.
    - c. Click the **Configuration required for Active Directory Domain Services** warning indicator.
    - d. From the All Servers Task Details and Notifications page, click the **Promote this server to a domain controller** action.
    - e. From the Deployment Configuration page, select **Add a new forest**. Specify the root domain name with a unique fully qualified domain name, for example, qawin01ldap.swg.usma.ibm.com, and then click **Next**
    - f. From the Domain Controller Options page, clear the **Domain Name System (DNS) server** option, and provide a password for Directory Services Restore Mode (DSRM). Click **Next**.
    - g. Accept the default NetBIOS name and click **Next**.
    - h. Accept the default paths for **AD DS** database, log files, and SYSVOL. Click **Next**.
    - i. Review the summary, click **Next**, and then click **Install**.
    - j. Restart the server

When the system restarts, you must include the domain that you specified with your login credentials. In this example, a QAWIN01LDAP domain was created. Specify QAWIN01LDAP\Administrator as the user when you log in to the system.
  3. Create containers, users, and groups for Maximo Asset Management.
    - a. Select **Control Panel > Administrative Tools > Active Directory Users and Computers**.
    - b. Select your server, right-click, and choose **New > Organizational Unit**.
    - c. Specify a name for the organizational unit, for example, SWG, and then click **OK**.
    - d. Select the new organizational unit that is located under your server, in this example, SWG, right-click, and choose **New > Organizational Unit**.
    - e. Specify a name for the organizational unit, for example, users, and then click **OK**.
    - f. Create another organizational unit under SWG and name it groups.
    - g. Right-click the **users** organizational unit, and click **New > User**.
    - h. Create a user who is called maxadmin. Specify maxadmin as the **First name** and **User logon name**. Click **Next**.
    - i. Provide a password for maxadmin. Click **Next** and then **Finish**.
    - j. Create two more users who are named mxintadm and maxreg.
    - k. Right-click the **groups** organizational unit and select and choose **New > Group**
    - l. Name the group maximousers and click **OK**.

- m. Right-click the maximousers group and select **Properties**.
- n. On the Members tab, click **Add**.
- o. Type maxadmin in the **Enter the object names to select** field, and then click **OK**. The maxadmin user is now a member of the maximousers Members list.
- p. Add the mxintadm and maxreg users to the maximousers group.
- q. Click **Apply**, then **OK**.

### What to do next

Microsoft Active Directory configuration is finished and you are now ready to configure the J2EE server to use Microsoft Active Directory.

## Manual configuration of the J2EE server

Manually configuring an existing J2EE server for use by Maximo Asset Management.

Manual configuration of the J2EE server is required if you choose to deploy Maximo Asset Management WebSphere Application Server Network Deployment and you choose to not have the Maximo Asset Management configuration program automatically configure it. You must complete the manual configuration before you use the Maximo Asset Management configuration program.

Maximo Asset Management requires Java 8. Java 8 must be installed and configured on the J2EE server you want to use with Maximo Asset Management.

### Manually configuring WebSphere Application Server Network Deployment

This section contains instructions for manually configuring an existing WebSphere Application Server Network Deployment for use by Maximo Asset Management.

You must manually configure WebSphere Application Server Network Deployment before you use the Maximo Asset Management configuration program if you do not want the Maximo Asset Management configuration program to configure it automatically.

#### Creating WebSphere Application Server Network Deployment profiles:

When manually installing WebSphere Application Server Network Deployment, profiles must be created before starting the Maximo Asset Management installation. WebSphere Application Server Network Deployment includes the **manageprofiles** command-line tool which you use to create profiles.

#### Before you begin

Ensure that you are familiar with the character limitations for commands or the shell you are using. In some cases, you might have to enter commands in order to avoid exceeding these limitations. See WebSphere Application Server Network Deployment product documentation for more information about entering lengthy commands on more than one line.

## About this task

The following commands can be useful for managing profiles:

Table 2. Profile commands

| Task                                                                 | Command                                                                                             |
|----------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------|
| Delete a profile                                                     | <code>WAS_HOME/bin/manageprofiles.[sh bat]</code><br><code>-delete -profileName profile name</code> |
| Refresh the profile registry (for example, after deleting a profile) | <code>WAS_HOME/bin/manageprofiles.[sh bat]</code><br><code>-validateAndUpdateRegistry</code>        |
| List existing profiles                                               | <code>WAS_HOME/bin/manageprofiles.[sh bat]</code><br><code>-listProfiles</code>                     |

`WAS_HOME` is equal to where WebSphere Application Server Network Deployment is installed, for example, `/opt/IBM/WebSphere/AppServer/` or `C:\Program Files\IBM\WebSphere\AppServer\`

To create WebSphere Application Server Network Deployment profiles, follow these steps:

### Procedure

1. Source the `setupCmdLine.[sh|bat]` script in the `bin` directory of the `WAS_HOME` folder to set the WebSphere Application Server Network Deployment environment to the configuration instance. `WAS_HOME` is typically in `/opt/IBM/WebSphere/AppServer` or `C:\Program Files\IBM\WebSphere\AppServer\`.
2. Create a profile ports file for the `ctgDmgr01` profile. This file is used with the **manageprofiles** command to set the ports used by this profile.

**Note:** It is important that you ensure no spaces appear after any value in this file. This circumstance can sometimes occur when cutting and pasting an example. If there is an extra space trailing any of the values WebSphere uses that space as the last character of that value. For example, you specify the value `WC_adminhost=9060`, but an extra space is typed after 9060. The value is interpreted as `WC_adminhost=9060&lt;sp>` (where `<sp>` represents a space character).

- a. Open a new text file named `_portdef_DMGr.props` and enter the following text:

```
CSIV2_SSL_SERVERAUTH_LISTENER_ADDRESS=9403
WC_adminhost=9060
DCS_UNICAST_ADDRESS=9352
BOOTSTRAP_ADDRESS=9809
SAS_SSL_SERVERAUTH_LISTENER_ADDRESS=9401
CELL_DISCOVERY_ADDRESS=7277
SOAP_CONNECTOR_ADDRESS=8879
ORB_LISTENER_ADDRESS=9100
CSIV2_SSL_MUTUALAUTH_LISTENER_ADDRESS=9402
WC_adminhost_secure=9043
```

- b. Place the file in the `WAS_HOME` directory.
3. Create the `ctgDmgr01` profile using the **manageprofiles** command. Type the following command, all on one line, with a space between each entry:

```
WAS_HOME/bin/manageprofiles.[sh|bat]
-create
-templatePath WAS_HOME/profileTemplates/dmgr
-hostName yourfullyqualifiedhost
-profileName ctgDmgr01
```

- ```
-profilePath WAS_HOME/profiles/ctgDmgr01
-portsFile WAS_HOME/_portdef_DMGr.props
-cellName ctgCell01
-nodeName ctgCellManager01
-enableAdminSecurity "false"
```
4. Ensure the ctgDmgr01 profile is configured to use Java 8.
 - a. List available Java JDKs to ensure Java 8 is installed on the system.


```
WAS_HOME/bin>managesdk.[sh|bat]
-listAvailable
-verbose
```
 - b. List the version of Java associated with ctgDmgr01.


```
WAS_HOME/bin/managesdk.[sh|bat]
-listEnabledProfile
-profileName ctgDmgr01
-verbose
```
 - c. If required, enable the ctgDmgr01 profile to use Java 8.


```
WAS_HOME/bin>managesdk.[sh|bat]
-enableProfile
-profileName ctgDmgr01
-sdkName 1.8_00
-enableServers
```
 5. Start the ctgDmgr01 server:


```
WAS_HOME/profiles/ctgDmgr01/bin/startManager.[sh|bat]
```
 6. Create a profile ports file for the ctgAppSrv01 profile. This file is used by the **manageprofiles** command to set the ports that are used by this profile.
 - a. Open a new text file named _portdef_AppSvr.props and enter the following text:


```
CSIV2_SSL_SERVERAUTH_LISTENER_ADDRESS=9201
DCS_UNICAST_ADDRESS=9353
NODE_DISCOVERY_ADDRESS=7272
NODE_IPV6_MULTICAST_DISCOVERY_ADDRESS=5001
BOOTSTRAP_ADDRESS=2809
SAS_SSL_SERVERAUTH_LISTENER_ADDRESS=9901
SOAP_CONNECTOR_ADDRESS=8878
NODE_MULTICAST_DISCOVERY_ADDRESS=5000
ORB_LISTENER_ADDRESS=9101
CSIV2_SSL_MUTUALAUTH_LISTENER_ADDRESS=9202
```
 - b. Place the file in the WAS_HOME directory.
 7. Create the ctgAppSrv01 profile using the **manageprofiles** command:


```
WAS_HOME/bin/manageprofiles.[sh|bat]
-create
-templatePath WAS_HOME/profileTemplates/managed
-hostName yourfullyqualifiedhost
-profileName ctgAppSrv01
-profilePath WAS_HOME/profiles/ctgAppSrv01
-cellName ctgNodeCell01
-nodeName ctgNode01
-portsFile WAS_HOME/_portdef_AppSvr.props
-dmgrHost yourfullyqualifiedhost
-dmgrPort 8879
-isDefault
```
 8. Ensure the ctgAppSrv01 profile is configured to use Java 8.
 - a. List available Java JDKs to ensure Java 8 is installed on the system.


```
WAS_HOME/bin>managesdk.[sh|bat]
-listAvailable
-verbose
```
 - b. List the version of Java associated with ctgAppSrv01.

```

WAS_HOME/bin/managesdk.[sh|bat]
-listEnabledProfile
-profileName ctgAppSrv01
-verbose

```

- c. If required, enable the ctgAppSrv01 profile to use Java 8.

```

WAS_HOME/bin>managesdk.[sh|bat]
-enableProfile
-profileName ctgAppSrv01
-sdkName 1.8_00
-enableServers

```

9. Start the ctgAppSrv01 node.

```

WAS_HOME/profiles/ctgAppSrv01/bin/startNode.[sh|bat]

```

10. Restart servers.

```

WAS_HOME/profiles/ctgDmgr01/bin/stopManager.[sh|bat]
WAS_HOME/profiles/ctgDmgr01/bin/startManager.[sh|bat]
WAS_HOME/profiles/ctgAppSrv01/bin/stopNode.[sh|bat]
WAS_HOME/profiles/ctgAppSrv01/bin/startNode.[sh|bat]

```

11. Start firststeps.[sh|bat] and select the **Installation Verification** option to confirm that your server has been properly installed and started.

```

WAS_HOME/profiles/ctgDmgr01/firststeps/firststeps.[sh|bat]

```

“Manually configuring Virtual Member Manager on WebSphere Application Server Network Deployment” on page 53

Some deployment environments require the manual configuration of Virtual Member Manager to secure Maximo Asset Management.

Manually creating a data source for the persistent store:

If you chose to manually configure WebSphere Application Server Network Deployment, you must create a data source in order to store JMS messages in a Db2 database.

About this task

You have the option of having WebSphere Application Server Network Deployment use a Db2 database to store JMS messages. For more information about WebSphere Application Server Network Deployment message storage, including the usage of products other than Db2, see http://www-01.ibm.com/support/knowledgecenter/SSLKT6/sslkt6_welcome.html.

To create a data source for the persistent store, complete the following steps:

Procedure

1. Create a system user and password on the server hosting the database server.
For example, a user named mxsibusr with a password of mxsibusr.
2. Create and configure the database.
 - a. Open Db2 Control Center.
 - b. Browse to the Databases folder listed under your system.
 - c. Right-click the Databases folder and select **Create Database > Standard**.
 - d. Create a database named maxsibdb using default settings.
 - e. After the database has been created, expand the maxsibdb database and select **User and Group objects**.
 - f. Right-click **DB Users** and select **Add**.
 - g. Select **mxsibusr** from the User menu.

- h. Grant all authorities to the mxsibusr except Security administrator authority.
- i. Click **Apply**.
- j. Verify that you can connect to the database using the mxsibusr user by right-clicking **maxsibdb** and selecting **Connect**.
3. Configure J2C authentication data and JDBC provider in WebSphere Application Server Network Deployment.
 - a. Open and login to the WebSphere Application Server Network Deployment administrative console.
 - b. Browse to **Security > Global Security**.
 - c. Under the Authentication header, click **Java Authentication and Authorization Service > J2C authentication data**.
 - d. Click **New**.
 - e. Complete the following fields in the User identity form.

Alias maxJaasAlias

User ID
 mxsibusr

Password
 Password you created for mxsibusr.

Description
 SIB database user alias.
 - f. Click **Apply**, and then click **Save**.
 - g. From the WebSphere Application Server administrative console, browse to **Resources > JDBC > JDBC Providers**.
 - h. Under **Scope**, click **Show scope selection drop-down list with the all scopes option**, select **Cell=ctgCell01**, and then, under **Preferences**, click **Apply**.
 - i. Click **New**.
 - j. Specify the following values, and then click **Apply**:

Database type
 DB2

Provider type
 DB2 Universal JDBC Driver Provider

Implementation type
 XA data source

Name maxJdbcProvider
 - k. Click **Next**.
 - l. Complete the WebSphere Application Server variable \${DB2UNIVERSAL_JDBC_DRIVER_PATH} field with a value of <WAS_HOME>ctgMX\lib. For example, C:\Program Files\IBM\WebSphere\AppServer\ctgMX\lib.
 - m. Click **Next**.
 - n. Click **Finish**.
 - o. Click **Save**.
4. Open a command prompt and copy <DB2_HOME>/java/db2jcc.jar and <DB2_HOME>/java/db2jcc_license_cu.jar to the <WAS_HOME>\ctgMX\lib directory. Go back to **Resources > JDBC > JDBC Providers > maxJdbcProvider**, and correct the class path if required for both db2jcc.jar

and db2jcc_license_cu.jar. Ensure that each jar file has the full path from \${DB2UNIVERSAL_JDBC_DRIVER_PATH}

5. Configure WebSphere Application Server:
 - a. From the WebSphere Application Server Network Deployment administrative console, browse to **Resources > JDBC > Data sources**.
 - b. Under **Scope**, click **Show scope selection drop-down list with the all scopes option**, select **Cell=ctgCell01**, and then, under **Preferences**, click **Apply**.
 - c. Click **New**.
 - d. Specify the following values:

Data source name
intjmsds

JNDI name
jdbc/intjmsds
 - e. From the Component-managed authentication alias and XA recovery authentication alias menu, select **maxJaasAlias**
 - f. Click **Next**.
 - g. Choose **Select an existing JDBC provider**, and then select **maxJdbcProvider** from the menu.
 - h. Click **Next**.
 - i. Specify the following values:

Database name
maxsibdb

Driver type
4

Server name
Specify the Db2 server host name.

Port number
Specify the Db2 port number. For example, 50005.
 - j. Ensure the **Use this data source in container managed persistence (CMP)** option is selected, and then click **Next**.
 - k. Click **Finish**.
 - l. Click **Save**.
6. Verify the data source by selecting **intjmsds**, and then clicking **Test Connection**.

Performing WebSphere Application Server Network Deployment configuration tasks:

Use this procedure to perform WebSphere Application Server Network Deployment configuration tasks.

About this task

If you elect to manually configure Maximo Asset Management middleware for use with Maximo Asset Management, you have to manually configure the WebSphere Application Server Network Deployment.

Procedure

1. Manually copy the keystore file from the WebSphere Application Server Network Deployment deployment manager host to a temporary directory on the Maximo Asset Management administrative system where you are installing Maximo Asset Management: `WAS_HOME/profiles/ctgDmgr01/etc/trust.p12`
2. Open a browser and access the administrative console by typing in the browser address bar: `http://server_name:9060/admin`. This URL address depicts the default port number (9060) and context (admin) for the administrative console. Enter a user name to log in. The browser is redirected to a secure port (9043).
3. Create the MXServer application server.
 - a. Expand **Servers > Server Types > WebSphere application servers**.
 - b. Click **New**.
 - c. Type **MXServer** and click **Next**.
 - d. Accept all default settings and click **Next**.
 - e. Accept default settings and click **Next**.
 - f. Click **Finish**.
 - g. Click **Preferences**.
 - h. Select the **Synchronize changes with Nodes** check box, and then click **Apply**.
 - i. Click **Save**.
 - j. Click **OK**.



Figure 4. Manually create the application server

4. Edit JVM Memory Settings and JVM Arguments for the application server.
 - a. Click **MXServer** in the main window.
 - b. From the Server Infrastructure group, expand the **Java and Process Management** link.
 - c. Click **Process Definition**.
 - d. Click **Java Virtual Machine**.
 - e. For **Initial Heap Size** and **Maximum Heap Size**, set these values to 4096.

- f. Enter the following values in the **Generic JVM arguments** field, using a space between each argument:

```
-Dsun.rmi.dgc.ackTimeout=10000
-Djava.net.preferIPv4Stack=true # for Windows
-Xdisableexplicitgc
-Xgcpolicy:gencon
-Xmn1024m      # Xmn1024m for 64-bit JVM
-Xlp64k        # AIX
```



Figure 5. Manually create the application server

- g. Click **OK**.
- h. Click **Save** in the messages box.
5. Edit thread pool settings for the application server.
 - a. Click **MXServer** from the **WebSphere application servers** panel.
 - b. From the Additional Properties group, click **Thread pools**.
 - c. Click **Default**. Set **Minimum Size** to 20. Set **Maximum Size** to 50. Set **Thread inactivity timeout** to 30000. Click **OK**.
 - d. Click **TCPChannel.DCS**. Set **Minimum Size** to 5. Set **Maximum Size** to 20. Set **Thread inactivity timeout** to 5000. Click **OK**.
 - e. Click **WebContainer**. Set **Minimum Size** to 50. Set **Maximum Size** to 50. Set **Thread inactivity timeout** to 30000. Click **OK**.




Figure 6. Edit thread pool settings for the application server

6. Edit JVM Memory Settings for the deployment manager.
 - a. From **System administration**, click **Deployment manager**.
 - b. From the Server Infrastructure group, expand the **Java and Process Management** link.
 - c. Click **Process Definition**.
 - d. Click **Java Virtual Machine**.
 - e. Scroll down and type 1024 for Initial Heap Size and 1024 for Maximum Heap Size and click **OK**.




Figure 7. Edit JVM Memory Settings for the deployment manager

- f. Click **Save** in the messages box.
7. Start the application server.
 - a. From **Servers > Server Types > WebSphere application servers**, click **Application servers**.
 - b. Select the check box for MXServer.
 - c. Click **Start**.
8. Identify the HTTP Transfer Port Numbers.
 - a. Expand **Servers > Server Types > WebSphere application servers**, and click **MXServer** from the main window.
 - b. Open the Web Container Settings and click **Web container transport chains**.
 - c. Note the default port number as it appears with WCInboundDefault (9080).




Figure 8. Identify the HTTP Transfer Port Numbers

9. Create the virtual host.
 - a. Expand **Environment**.
 - b. Click **Virtual Hosts**.
 - c. Click **New**.
 - d. In the General Properties section, type `maximo_host` in the Name box.
 - e. Click **Apply**.
 - f. Click **Save**.
 - g. Click **OK**.
 - h. From the Virtual Hosts window, click **maximo_host**.
 - i. Click the **Host Aliases** link.
 - j. Click **New**.
 - k. Type * (asterisk) for host name and type the HTTP port number (by default 80).
 - l. Click **OK**.
 - m. Click **New**.
 - n. Type * (asterisk) for host name and type 9061 for the port number.
 - o. Click **OK**.
 - p. Click **New**.
 - q. Type * (asterisk) for host name and type 9443 for the port number.
 - r. Click **OK**.
 - s. Click **New**.
 - t. Type * (asterisk) for host name and type 9080 for the port number.
 - u. Click **OK**.
 - v. Click **New**.
 - w. Type * (asterisk) for host name and type 9044 for the port number.
 - x. Click **OK** and then click **Save**.




Figure 9. Create the virtual host

10. Enable automatic startup of the application server when the node agent is started.
 - a. Expand **Servers > Server Types > WebSphere application servers**.
 - b. Click **MXServer** in the main window.
 - c. From the Server Infrastructure group, expand **Java and Process Management**.
 - d. Click **Monitoring Policy**.
 - e. Set Node restart state to **RUNNING** and click **OK**.
 - f. Click **Save** in the messages box.




Figure 10. Enable automatic startup of the application server when the node agent is started

Creating a Windows service for the node agent:

You can create a Windows service for starting the WebSphere Application Server Network Deployment node agent.

About this task

Although not required, you can optionally start the node agent as a Windows service.

If you used the middleware installation program to install WebSphere Application Server Network Deployment v7, this step has already been performed by the middleware installation program.

Procedure

1. Open a command prompt.
2. Change directory to <WAS_HOME>\bin.
3. Type the following command with no line breaks (case-sensitive).

```
WASService
-add NodeAgent
-serverName nodeagent
-profilePath "C:\IBM\WebSphere\AppServer\profiles\ctgAppSrv01"
-wasHome "C:\IBM\WebSphere\AppServer"
-logRoot "C:\IBM\WebSphere\AppServer\profiles\ctgAppSrv01\logs\nodeagent"
-logFile "C:\IBM\WebSphere\AppServer\profiles\ctgAppSrv01\logs\nodeagent\
startServer.log"
-restart true
```

4. Close the Command Prompt.

Manually configuring JMS queues:

This procedure provides details on steps to configure JMS queues, which must be completed before using the product installation program.

About this task

During the installation process, the Maximo Asset Management installation program provides you with the option of automatically configuring Maximo Asset Management middleware. If you elect to have the Maximo Asset Management installation program automatically configure Maximo Asset Management middleware, it creates and configures JMS message queues for you. If you elect to manually configure Maximo Asset Management middleware for use with Maximo Asset Management, you must manually configure these message queues.

To configure the JMS queues, complete the following steps:

Procedure

1. Start the WebSphere Application Server Network Deployment application server.
2. Start Internet Explorer and open the WebSphere Application Server Network Deployment administrative console by typing the following URL:

`http://<server_name>:<port_number>/ibm/console`

For example, enter a URL like the following sample URL:

`http://localhost:9060/ibm/console`

3. At the login screen, enter your user ID, then click **Log in**. This action opens the Welcome screen for the WebSphere Application Server Network Deployment administrative console.
4. Click **Service Integration > Buses** to open the Buses dialog. A bus is a group of interconnected servers and clusters that have been added as members of the bus.
5. Click **New** to open the **Create a new Service Integration Bus** panel where you can add a new service integration bus.
6. Enter `intjmsbus` as the name of the new bus in the Name field.
7. Clear the **Bus security** check box. If you leave this box checked, `intjmsbus` inherits the Global Security setting of the cell.
8. Click **Next**.
9. Click **Finish**.
10. Click **Save**. This step propagates the JMS bus setup to the cluster configuration.

Adding a server to the service integration bus:

A server must be defined for the service integration bus.

About this task

Complete the following steps to add a server to the service integration bus:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Service Integration > Buses** to open the Buses dialog box.
2. Click `intjmsbus` to open the **Buses > intjmsbus** dialog box.
3. Under Topology, click **Bus members**.
4. In the **Buses > intjmsbus > Bus members** dialog box, click **Add** to open the Add a new bus member dialog box.
5. Select the **Server** option, and select the server name `ctgNode01:MXServer` to add to the bus, and then click **Next**.
6. Check that the **File store** radio button is selected, and then click **Next**.
7. From the Configure file store panel, click **Next**.
8. From the Tune application server for messaging performance panel, click **Next**.
9. Click **Finish**.
10. Click **Save**.
11. Select `intjmsbus`.
12. Change the value of the **Default messaging engine high message threshold** field to a minimum value of 500,000 messages, and then click **Apply**.

If the number of messages awaiting processing exceeds the High Message Threshold you set, the application server limits the addition of new messages in the processing queues.

Depending on your message requirements, you can enter a higher message threshold value. You can determine an optimal message threshold setting by monitoring the messaging in/out queues and the impact of the message threshold setting on system performance. You might, for example, lower the threshold value if a higher value is degrading system performance.

If you decide to change the High message threshold setting after the initial configuration, you must open the Additional Properties menu in the administrative console and change the threshold value for each child configuration.

13. Click **Save**.

Creating the service integration bus destination for the continuous inbound (CQINBD) queue:

You must create a service integration bus destination for the continuous inbound (CQINBD) queue.

About this task

To add a logical address for the continuous inbound bus destination queue (CQINBD) within the JMS bus, complete the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment Administrative Console, click **Service Integration** > **Buses** to open the Buses dialog box.
2. Click **intjmsbus** to open the **Buses** > **intjmsbus** dialog box.
3. Click **Destinations** under Destination resources to open the **Buses** > **intjmsbus** > **Destinations** dialog box.
A bus destination, for example CQINBD, is a virtual place within a service integration bus where applications can attach and exchange messages.
4. Click **New** to open the Create new destination dialog box.
5. Leave **Queue** checked as the destination type, and click **Next** to open the Create new queue dialog box.
6. Type CQINBD in the Identifier field and Continuous Queue Inbound in the Description field, then click **Next** to open the Create a new queue for point-to-point messaging dialog box.
7. Select the Bus Member pull-down and choose **Node=ctgNode01:Server=MXServer** as the bus member that will store and process messages for the CQINBD bus destination queue.
8. Click **Next** to open the Confirm queue creation dialog box.
9. Review your selections, then click **Finish** to complete the creation of the CQINBD bus destination queue.
10. Navigate the path **Buses** > **intjmsbus** > **Destinations**, then click **CQINBD** to open the configuration dialog box.
11. Click **None** as the Exception destination value.
12. Verify **Keep count of failed deliveries per message** is enabled.
13. Click **Apply**.
14. Click **Save**.

Creating the service integration bus destination for the sequential inbound (SQINBD) queue:

You must create the service integration bus destination for the sequential inbound (SQINBD) queue.

About this task

To add a logical address for the sequential inbound bus destination queue (SQINBD) within the service integration bus, complete the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment Administrative Console, click **Service Integration** > **Buses** to open the Buses dialog box.
2. Click **intjmsbus** to open the **Buses** > **intjmsbus** dialog box.
3. Click **Destinations** under Destination resources to open the **Buses** > **intjmsbus** > **Destinations** dialog box. A bus destination is a virtual place within a service integration bus where applications can attach and exchange messages.
4. Click **New** to open the Create new destination dialog box.
5. Leave **Queue** checked as the destination type, and click **Next** to open the Create new queue dialog box.
6. Enter SQINBD in the Identifier field and Sequential Queue Inbound in the Description field, then click **Next** to open the Create a new queue for point-to-point messaging dialog box. Note that you must use this value and it must contain only uppercase letters.
7. Select the Bus Member pull-down and choose **Node=ctgNode01:Server=MXServer**
8. Click **Next** to open the Confirm queue creation dialog box.
9. Review your selections, then click **Finish** to complete the creation of the SQINBD bus destination queue.
10. Navigate the path **Buses** > **intjmsbus** > **Destinations**, then click **SQINBD** to open the configuration dialog box.
11. Click **None** as the Exception destination value.
12. Verify **Keep count of failed deliveries per message** is enabled.
13. Click **Apply**.
14. Click **Save**.

Creating the service integration bus destination for the sequential outbound (SQOUTBD) queue:

You must create the service integration bus destination for the sequential outbound (SQOUTBD) queue.

About this task

To add a logical address for the sequential outbound bus destination queue (SQOUTBD) within the service integration bus, complete the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Service Integration** > **Buses** to open the Buses dialog box.
2. Click **intjmsbus** to open the **Buses** > **intjmsbus** dialog box.
3. Click **Destinations** under Destination resources to open the **Buses** > **intjmsbus** > **Destinations** dialog box. A bus destination, for example SQOUTBD, is a virtual place within a service integration bus where applications can attach and exchange messages.
4. Click **New** to open the Create new destination dialog box.

5. Leave **Queue** checked as the destination type, and click **Next** to open the Create new queue dialog box.
6. Enter SQOUTBD in the Identifier field and Sequential Queue Outbound in the Description field, then click **Next** to open the Create a new queue for point-to-point messaging dialog box. You must use this value and it must contain only uppercase letters.
7. Select the Bus Member menu and choose **Node=ctgNode01:Server=MXServer** as the bus member that stores and processes messages for the SQOUTBD bus destination queue.
8. Click **Next** to open the Confirm queue creation dialog box.
9. Review your selections, then click **Finish** to complete the creation of the queue.
10. Navigate the path **Buses > intjmsbus > Destinations**, then click **SQOUTBD** to open the configuration dialog box where you must make the following changes:
11. Click **None** as the Exception destination value.
12. Verify **Keep count of failed deliveries per message** is enabled.
13. Click **Apply**.
14. Click **Save**.

Creating the JMS connection factory:

Add a connection factory for creating connections to the associated JMS provider of point-to-point messaging queues.

About this task

To create the JMS connection factory, complete the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Connection factories**.
2. From the **Scope** drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the Default Messaging Provider is selected and click **OK**.
5. Enter the following information:
 - Name** Enter intjmsconfact.
 - JNDI name**
Enter jms/maximo/int/cf/intcf.
 - Bus name**
Select **intjmsbus**.
6. Click **Apply**.
7. Click **Save**.

Creating the continuous inbound (CQIN) JMS queue:

You must create a JMS queue (CQIN) as the destination for continuous inbound point-to-point messages.

About this task

To create the CQIN JMS queue, complete the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the Scope drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the Default Messaging Provider is selected and click **OK**.
5. Enter the following information, and click **OK**.

Name Enter CQIN.

This value must contain only uppercase letters.

JNDI name

Enter `jms/maximo/int/queues/cqin`

Bus name

Select **intjmsbus**.

Queue name

Select **CQINBD**.

6. Click **OK**.
7. Click **Save**.

Creating the sequential inbound (SQIN) JMS queue:

You must create a JMS queue (SQIN) as the destination for sequential inbound point-to-point messages.

About this task

To create the SQIN JMS queue, complete the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the Scope drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the Default Messaging Provider is selected and click **OK**.
5. Enter the following information, and click **OK**.

Name Enter SQIN.

This value must contain only uppercase letters.

JNDI name

Enter `jms/maximo/int/queues/sqin`

Bus name

Select **intjmsbus**.

Queue name

Select **SQINBD**.

6. Click **OK**.
7. Click **Save**.

Creating the sequential outbound (SQOUT) JMS queue:

You must create a JMS queue (SQOUT) as the destination for sequential outbound point-to-point messages.

About this task

To create the SQOUT JMS queue, complete the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the Scope drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the Default Messaging Provider is selected and click **OK**.
5. Enter the following information, and click **OK**.

Name Enter SQOUT.

This value must contain only uppercase letters.

JNDI name

Enter jms/maximo/int/queues/sqout

Bus name

Select **intjmsbus**.

Queue name

Select **SQOUTBD**.

6. Click **OK**.

7. Click **Save**.

Creating JMS activation specification for the continuous inbound queue (CQIN):

You must activate the continuous inbound queue (CQIN) before it can receive messages.

About this task

Complete the following steps to activate the CQIN queue:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Activation Specifications**.
2. From the Scope drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Select **Default messaging provider** and then click **OK**.
5. Enter the following information, and then click **OK**.

Name intjmsact

This value is case-sensitive. This value must be lowercase.

JNDI name

intjmsact

Destination type

Queue

Destination JNDI name

jms/maximo/int/queues/cqin

Bus name

intjmsbus

Maximum concurrent MDB invocations per endpoint

10

6. Click **OK**, and then click **Save**.

Error queues:

You must create an error queue that receives redirected messages from the continuous queue (CQIN).

When the messages go in error, the error queue receives redirected messages from the continuous queue (CQIN).

Creating the service integration bus destination for the inbound error queue (CQINERRBD) queue:

You must add a logical address for the inbound error queue (CQINERRBD) queue within the JMS bus.

About this task

Perform the following steps:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Service Integration > Buses** to open the Buses dialog box.
2. Click **intjmsbus** to open the **Buses > intjmsbus** dialog box.
3. Click **Destinations** under Destination resources to open the **Buses > intjmsbus > Destinations** dialog box. A bus destination is a virtual place within a service integration bus where applications can attach and exchange messages.
4. Click **New** to open the Create new destination dialog box.
5. Leave **Queue** checked as the destination type, and click **Next** to open the Create new queue dialog box.
6. Enter CQINERRBD in the Identifier field and Error Queue Inbound in the Description field, then click **Next** to open the Create a new queue for point-to-point messaging dialog box. You must use this value and it must contain only uppercase letters.
7. From the Bus Member menu, select **Node=ctgNode01:Server=MXServer**
8. Click **Next** to open the Confirm queue creation dialog box.
9. Review your selections, then click **Finish** to create the CQINERRBD bus destination queue.
10. Select **Buses > intjmsbus > Destinations**, then click **CQINERRBD** to open the configuration dialog box where you must make the following changes:
 - a. Select the **Specify** option and enter CQINERRBD as the exception destination value.
 - b. Change the Maximum failed deliveries value to 5.

This option is the maximum number of times you want the system to process a failed messaging attempt before forwarding the message to the exception destination.

c. Verify **Keep count of failed deliveries per message** is enabled.

11. Click **Apply**.
12. Click **Save**.
13. From the WebSphere Application Server Network Deployment administrative console, click **Service Integration** > **Buses** to open the Buses dialog box.
14. Click **intjmsbus** to open the **Buses** > **intjmsbus** dialog box.
15. Click **Destinations** under Destination resources to open the **Buses** > **intjmsbus** > **Destinations** dialog box.
16. Select **CQINBD**.
17. Specify CQINERRBD as the exception destination. Set the Maximum failed deliveries value to 5.
18. Click **OK**.
19. Click **Save**.

Creating the error (CQINERR) JMS queue:

After creating the Error Queue Bus Destination, you create the Error queue.

About this task

To create the Error queue, complete the following steps.

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources** > **JMS** > **Queues**.
2. From the Scope drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the Default Messaging Provider is selected and click **OK**.
5. Enter the following information, and click **OK**.

Name Enter CQINERR.

This value must contain only uppercase letters.

JNDI name

Enter jms/maximo/int/queues/cqinerr

Bus name

Select **intjmsbus**.

Queue name

Select **CQINERRBD**.

6. Click **OK**.
7. Click **Save**.

Creating JMS activation specification for the inbound error queue (CQINERR):

You must activate the continuous inbound queue (CQINERR) before it can receive messages.

About this task

Complete the following steps to activate the CQINERR queue:

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Activation Specifications**.
2. From the Scope menu, select **Cell=ctgCell01**, and then click **Apply**.
3. Click **New** to complete the General Properties section for the new JMS activation specification.
4. Click **OK**.
5. Enter the following information, and click **OK**.

Name Enter intjmsacterr.

This value must only contain lowercase letters.

JNDI name

Enter intjmsacterr.

This value must be the same as the one used for the **Name** field.

Destination type

Enter Queue.

Destination JNDI name

jms/maximo/int/queues/cqinerr

Bus name

intjmsbus

Maximum concurrent MDB invocations per endpoint

10

6. Click **OK**.
7. Click **Save**.
8. Ensure that you stop all IBM-related processes and daemons.
9. You must now restart these processes for the update to take effect.
10. Start the bus member for the ctgNode MXServer intjmsbus if it is not started. If you cannot start ctgNode MXServer intjmsbus, restart MXServer under **Servers > Application servers**.

Manually configuring Virtual Member Manager on WebSphere Application Server Network Deployment:

Some deployment environments require the manual configuration of Virtual Member Manager to secure Maximo Asset Management.

Before you begin

For a review of Maximo Asset Management security options, see the security planning information.

Important: Before you begin this procedure, ensure that you have a wasadmin user ID created in your LDAP repository.

If you intend to configure Virtual Member Manager to use SSL with a federated LDAP repository, it must be done only after a successful Maximo Asset Management installation and configuration. If Virtual Member Manager is

configured to use SSL with a federated LDAP repository before completing the Maximo Asset Management configuration, the configuration fails. Do not configure a Virtual Member Manager LDAP federated repository to use SSL with an LDAP directory before configuration Maximo Asset Management. Configure SSL after the Maximo Asset Management configuration program has completed successfully.

About this task

During the configuration process, the Maximo Asset Management configuration program provided you with the option of automatically configuring Maximo Asset Management middleware. If you elected to have the Maximo Asset Management configuration program automatically configure Maximo Asset Management middleware, then it will, among other tasks, perform Virtual Member Manager configuration for you. If you elected to manually configure Maximo Asset Management middleware for use with Maximo Asset Management, you must manually configure Virtual Member Manager.

Virtual Member Manager provides you with the ability to access and maintain user data in multiple repositories, and federate that data into a single virtual repository. The federated repository consists of a single named realm, which is a set of independent user repositories. Each repository can be an entire external repository or, in the case of LDAP, a subtree within that repository. The root of each repository is mapped to a base entry within the federated repository. The root is a starting point within the hierarchical namespace of the virtual realm.

To add an LDAP directory to the Virtual Member Manager virtual repository, you must first add the LDAP directory to the list of repositories available for configuration for the federated repository. You must then add the root of baseEntries to a search base within the LDAP directory. Multiple base entries can be added with different search bases for a single LDAP directory.

The values provided here are example purposes only. If you are using IBM Security Directory Server, enter the values used during the installation and configuration of IBM Security Directory Server. If you are configuring Virtual Member Manager to use Microsoft Active Directory, substitute values where appropriate in this procedure. You must modify the VMMSYNC cron task accordingly.

To add the IBM Security Directory Server or Microsoft Active Directory to VMM, complete the following steps:

Procedure

1. Start the WebSphere Application Server Network Deployment application server.
2. Start Internet Explorer and open the WebSphere Application Server Network Deployment administrative console by typing the following URL:
`http://<server_name>:<port_number>/admin`
For example, enter a URL like the following sample URL:
`http://localhost:9060/admin`
3. At the login screen, enter your user ID, then click **Log in**. This action opens the Welcome screen for the WebSphere Application Server Network Deployment administrative console.
4. Select **Security > Global security**.

5. Locate the User account repository area and pick **Federated repositories** from the Available realm definitions field, and then click **Configure**.
6. Click **Add repositories** located under Repositories in the realm.
7. Click **New repository > LDAP repository** to create new repository definition under the current default realm.
8. Enter the following values, click **Apply**, and then click **Save**.

Repository identifier

For IBM Security Directory Server, enter ISMITDS.

For Microsoft Active Directory, enter ISMMSAD .

Directory type

For IBM Security Directory Server, select IBM Tivoli Directory Server.

For Microsoft Active Directory, select Microsoft Windows Server 2012 Active Directory.

Primary host name

Enter the fully qualified host name or IP address of the directory server.

Port Enter 389.

Support referrals to other LDAP servers

Set this value to ignore.

Bind distinguished name

For IBM Security Directory Server, enter cn=root.

For Microsoft Active Directory, enter
CN=Administrator,CN=Users,DC=ism76,DC=com.

Bind password

Enter the password for the bind distinguished name.

Certificate mapping

Select EXACT_DN




Figure 11. New Repository

9. Enter the following values, click **Apply**, and then click **Save**.

Repository

For IBM Security Directory Server, select ISMITDS.

For Microsoft Active Directory, select ISMMSAD .

Unique distinguished name of the base entry (or parent) entry in federated repositories

For IBM Security Directory Server, enter ou=SWG,o=IBM,c=US.

For Microsoft Active Directory, enter DC=ism76,DC=com.

Distinguished name in the repository is different

This value is optional. You need to provide this value if it differs from the base entry in the repository you are adding.

For IBM Security Directory Server, enter ou=SWG,o=IBM,c=US.

For Microsoft Active Directory, enter DC=ism76,DC=com.

10. From the Federated repositories configuration area, enter the following values, click **Apply**, and then click **Save**:

Realm name

Enter ISMRealm.

Primary administrative user name

Enter wasadmin. This value must be a valid user from the configured LDAP repository.

Server user identity

Select **Automatically generated server identity**.

Ignore case for authorization

Select this check box.

11. Click **Supported entity types**, and then click **PersonAccount**.

12. From the PersonAccount configuration area, enter the following values:

Entity type

Verify that the value is **PersonAccount**.

Base entry for the default parent

For IBM Security Directory Server, enter `ou=users,ou=SWG,o=IBM,c=US`.

For Microsoft Active Directory, enter `CN=Users,DC=ism76,DC=com`.

Relative Distinguished Name properties

Enter `uid`.

13. Click **OK** and then click **Save**.
14. Click **Supported entity types**, and then click **Group**.
15. From the Group configuration area, enter the following values:

Entity type

Verify that the value is **Group**.

Base entry for the default parent

For IBM Security Directory Server, enter
`ou=groups,ou=SWG,o=IBM,c=US`.

For Microsoft Active Directory, enter
`ou=groups,CN=Groups,DC=ism76,DC=com`.

Relative Distinguished Name properties

Enter `cn`.

16. Click **OK** and then click **Save**.
17. Click **Supported entity types**, and then click **OrgContainer**.
18. From the OrgContainer configuration area, enter or verify the following values:

Entity type

Verify that the value is **OrgContainer**.

Base entry for the default parent

For IBM Security Directory Server, enter `ou=SWG,o=IBM,c=US`.

For Microsoft Active Directory, enter `DC=ism76,DC=com`.

Relative Distinguished Name properties

Enter `o;ou;dc;cn`.

19. Click **OK** and then click **Save**.
20. Browse to **Security > Global security**.
21. From the Global security configuration page, complete the following:
 - a. Enable **Enable administrative security**.
 - b. Enable **Enable application security**.
 - c. Clear the option for **Use Java 2 security to restrict application access to local resources**.
 - d. From Available realm definition, select **Federated repositories**.
 - e. Click **Set as current**.
22. Click **Apply**, and then click **Save**.
23. Restart WebSphere Application Server Network Deployment and the managed nodes by running the following commands:
 - a. `<WAS_HOME>\profiles\ctgDmgr01\bin\stopManager.bat`
 - b. `<WAS_HOME>\profiles\ctgAppSrv01\bin\stopNode.bat`
 - c. `<WAS_HOME>\profiles\ctgDmgr01\bin\startManager.bat`

d. <WAS_HOME>\profiles\ctgAppSrv01\bin\startNode.bat

Note: Substitute UNIX path and file extension values where appropriate.
“Performing WebSphere Application Server Network Deployment configuration tasks” on page 37
Use this procedure to perform WebSphere Application Server Network Deployment configuration tasks.
“Manually configuring Microsoft Active Directory version 2012” on page 30
You can manually configure Microsoft Active Directory for use with Maximo Asset Management.

Running the Maximo Asset Management 7.6.1 installation program

Use the Maximo Asset Management version 7.6.1 installation program to install Maximo Asset Management version 7.6.1.

Before you begin

Maximo Asset Management version 7.6.1 must be installed in a separate location on the administration workstation to any existing Maximo Asset Management versions.

About this task

In order to install Maximo Asset Management version 7.6.1, run the Maximo Asset Management version 7.6.1 installation program on the Maximo Asset Management administrative system.

Procedure

1. Log in to the Maximo Asset Management administrative workstation. If you run the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Start the Maximo Asset Management launchpad.

Option	Description
Windows	launchpad64.exe
Linux or UNIX	./launchpad.sh

- a. Select a language for the installation session and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the **Install IBM Maximo Asset Management** panel, select **IBM Maximo Asset Management v7.6.1** and then click **Install**.
3. In the package selection panel, click **Next**.
 4. In the package prerequisite validation panel, review the results of the prerequisite check, and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.
 5. In the license agreement panel, review the license information for each package being installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.

6. In the Installation Manager installation location panel, specify path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.
7. In the package installation location panel, select the IBM Tivoli's process automation suite package group, specify the path information for the Maximo Asset Management version 7.6.1 installation directory, and then click **Next**.
8. In the package summary panel, review the information for the planned installation, and then click **Install**. If you install in a non-English environment, you might notice the environment summary is listed as English. You configure supported languages for Maximo Asset Management later with the Maximo Asset Management configuration program.
9. After the installation is complete, select the option to start the Maximo Asset Management version 7.6.1 configuration program, and then click **Finish**. The Maximo Asset Management version 7.6.1 installation program exits and the Maximo Asset Management version 7.6.1 configuration program is started automatically.

What to do next

Use the Maximo Asset Management version 7.6.1 configuration program to configure Maximo Asset Management version 7.6.1.

Configuring Maximo Asset Management version 7.6.1 with manually configured middleware

This procedure explains how to use the Maximo Asset Management version 7.6.1 configuration program to configure Maximo Asset Management version 7.6.1.

Procedure

1. If the Maximo Asset Management version 7.6.1 configuration program is not open, start it from the Maximo Asset Management launchpad. In the launchpad navigation pane, click **Configure Product**, specify Maximo Asset Management installation location, and then click **Launch the Tivoli's Process Automation Suite configuration program**.
2. In the IBM Maximo Asset Management configuration operations page, click **Configure a New Deployment**.
3. In the Define Deployment Environment panel, specify information about Db2 and WebSphere Application Server Network Deployment servers you installed and prepared. Select the **WebSphere is already configured** option. After you define your deployment environment, click **Finish**.
4. In the Configure General Product Information panel, review summary details about the product components you are installing. Specify the appearance and navigation features for your product, add an e-mail address to receive workflow messages, and choose whether or not to deploy sample data.
5. In the Configure the DB2 Instance panel, specify information about the Db2 instance for Maximo Asset Management.
6. In the Configure the DB2 Database panel, specify information about the Db2 database for Maximo Asset Management.

7. In the Configure the Application Server panel, specify information for the WebSphere Application Server Network Deployment server you installed. Indicate whether you want to store JMS messages originating from the integration adapter.
8. In the Configure Application Security panel, choose a security model for Maximo Asset Management. If you choose a security model that includes a directory server, specify information about the directory for the virtual member manager. Enter the user names and passwords for users that must be created for Maximo Asset Management.
9. Choose the base language and any additional languages you want to install.
10. In the Apply Deployment Operations panel, specify user interface preferences, select all available deployment operations, and then click **Finish**.

Results

Maximo Asset Management version 7.6.1 is installed and configured to use WebSphere Application Server Network Deployment and Db2.

Creating the NOTF JMS queue

You must create a JMS queue NOTF for notifications.

About this task

You must create a JMS queue called NOTF to enable notifications. If you do not use the Maximo Asset Management configuration program to automatically configure WebSphere Application Server Network Deployment, you must create this queue manually.

For Maximo Asset Management multitenancy environments, the system provider must create the NOTF queue manually to enable notifications for each tenant. These queues cannot be created automatically by using Maximo Asset Management installation and configuration programs.

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the **Scope** drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the default messaging provider is selected and then click **OK**.
5. Enter the following information, and then click **OK**.

Name NOTF.

This value must contain only uppercase letters.

JNDI name

jms/maximo/int/queues/notf

Bus name

intjmsbus.

Queue name

CQINBD.

6. Click **OK** and then click **Save**.

Creating the NOTFERR JMS queue

After creating the Error Queue Bus Destination, you create the NOTFERR Error queue for notification error handling.

About this task

You must create a JMS queue called NOTFERR to enable notification error handling. If you do not use the Maximo Asset Management configuration program to automatically configure WebSphere Application Server Network Deployment, you must create this queue manually.

For Maximo Asset Management multitenancy environments, the system provider must create the NOTF queue manually to enable notifications for each tenant. These queues cannot be created automatically by using Maximo Asset Management installation and configuration programs.

Procedure

1. From the WebSphere Application Server Network Deployment administrative console, click **Resources > JMS > Queues**.
2. From the **Scope** drop-down list, select **Cell=ctgCell01**.
3. Click **New**.
4. Verify that the default messaging provider is selected and then click **OK**.
5. Enter the following information, and then click **OK**.

Name Enter NOTFERR.

This value must contain only uppercase letters.

JNDI name

Enter `jms/maximo/int/queues/notferr`

Bus name

Select `intjmsbus`.

Queue name

Select `CQINERRBD`.

6. Click **OK** and then click **Save**.

Chapter 5. Update the application database with the UpdateDB Lite command

UpdateDB Lite splits the tasks of preparing class files and updating the database in Maximo Asset Management.

In Maximo Asset Management 7.6.1, you can minimize downtime by using new programs to manually perform configuration steps. Tasks that are performed by the UpdateDB Lite program, preparation of product class files and database updates, are split into two separate commands. These commands include pre-processing and post-processing.

Pre-processing tasks prepare class files before they are built into the application EAR files without stopping the application server. The updatedb command can also perform this work, but it stops the application server.

In post-processing, UpdateDB Lite can perform updates to the database, but the application server must be stopped before you run the command. UpdateDB and UpdateDB Lite use the exact same parameters.

The Maximo Asset Management 7.6.1 configuration tool uses the UpdateDB to complete configuration.

Updating the database with UpdateDB Lite

Using UpdateDB Lite to update the database can reduce application downtime.

Before you begin

Use Installation Manager to install Maximo Asset Management 7.6.1. Do not use the Maximo Asset Management configuration tool to update the database or build and deploy application EAR files.

Procedure

1. Open the config tool.
2. Click **Update Database with UpdateDB Lite Feature**.
3. Verify the application version and current state.
4. Select to run the pre-processing or post-processing options, and click **Finish**.

Results

If post-processing options are selected, the Maximo application closes until the updates to the database are complete.

Chapter 6. Deploying in a cluster environment

Use the Maximo Asset Management installation and configuration programs to install and automatically configure Maximo Asset Management in a WebSphere Application Server Network Deployment cluster configuration.

About this task

In this scenario, you use the Maximo Asset Management installation and configuration programs to install and automatically configure new instances of the following components in a cluster configuration:

- Db2
- WebSphere Application Server Network Deployment
- Maximo Asset Management

You use the Maximo Asset Management installation program to install Maximo Asset Management and the middleware you want to use in your deployment. You then use the Maximo Asset Management configuration program to configure both middleware and Maximo Asset Management.

You can use the Maximo Asset Management installation program to install Db2. You then use the Maximo Asset Management configuration program to automatically configure it.

You can use the roadmap of tasks to automatically configure middleware and deploy Maximo Asset Management in a cluster environment.




Figure 12. Deploying Maximo Asset Management using automatic middleware configuration

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment

Configuring SSL between Microsoft Active Directory and WebSphere Application Server Network Deployment enables the Maximo Asset Management configuration program to automatically create users and groups in the directory. Users and groups must be created in the directory if you plan to use a directory server for

Maximo Asset Management authentication and authorization. If you plan to use Maximo Asset Management application security for authentication and authorization, you do not need configure SSL for a directory server.

About this task

To enable the configuration program to automatically create users and groups within Microsoft Active Directory, you must configure SSL communication between Microsoft Active Directory and WebSphere Application Server Network Deployment. This procedure is only required if you choose to allow the configuration program to automatically configure WebSphere Application Server Network Deployment. You also want the configuration program to automatically create users in Microsoft Active Directory.

You must enable SSL for Microsoft Active Directory, generate a certificate, and then add that certificate to WebSphere Application Server Network Deployment.

Changing the name or domain of the certificate authority at any point invalidates certificates previously issued from that authority.

Ensure that you have host name resolution setup properly in your environment. Communication failures occur if the system hosting Microsoft Active Directory cannot resolve host names for systems that have been issued certificates.

Installing Db2 v11.1 using the Maximo Asset Management version 7.6.1 installation program

Use the Maximo Asset Management version 7.6.1 installation program to install Db2 v11.1.

Procedure

1. Log in to the target system as a user with administrative authority. If you are running the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Run the Installation Manager from the following directory:

Option	Description
Windows	Start > All Programs > IBM Installation Manager > IBM Installation Manager
UNIX	In the /opt/IBM/InstallationManager/eclipse directory, run the IBMIM command.

- a. Select a language for the installation and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the Install IBM Maximo Asset Management panel, select **IBM Db2 v11.1** and then click **Install**.
3. In the package selection panel, click **Next**.
 4. In the package prerequisite validation panel, review the results of the prerequisite check and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.

5. In the license agreement panel, review the license information for each package being installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.
6. In the Installation Manager installation location panel, specify path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.
7. In the package installation location panel, select a package group, specify the path information for its installation directory, and then click **Next**.
8. In the package features panel, leave all default options checked, and then click **Next**.
9. In the package configuration panel, specify configuration information for Db2 v11.1, and then click **Next**.
10. In the package summary panel, review the information for the planned installation, and then click **Install**.

Installing WebSphere Application Server Network Deployment v9.0.0.7 using the Maximo Asset Management version 7.6.1 Installation Manager

You can use the IBM Launchpad program to install WebSphere Application Server Network Deployment v9.0.0.7.

Procedure

1. Log in to the target system as a user with administrative authority. If you are running the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Start the Maximo Asset Management launchpad.

Option	Description
Windows	launchpad64.exe
Linux or UNIX	./launchpad.sh

- a. Select a language for the installation and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the Install IBM Maximo Asset Management panel, select **IBM WebSphere Application Server Network Deployment v9.0.0.7** and then click **Install**. During the installation of WebSphere Application Server Network Deployment, install Java v8. When you install Java v8, the configuration program configures IBM Maximo Asset Management to use Java v8.
3. In the package selection panel, click **Next**.
 4. In the package prerequisite validation panel, review the results of the prerequisite check, and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.

5. In the license agreement panel, review the license information for each package that is to be installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.
6. In the Installation Manager installation location panel, specify the path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.
7. In the package installation location panel, select a package group, specify path information for its installation directory. Repeat this process for each package group that is listed and then click **Next**.
8. In the package translations panel, specify language support for WebSphere Application Server Network Deployment, and then click **Next**.
9. In the package features panel, leave all default options selected, and then click **Next**.
10. In the package configuration panel, specify configuration information for IBM HTTP Server, and then click **Next**.
11. In the package summary panel, review the information for the planned installation, and then click **Install**.
12. After the installation is complete, select the option to start the Maximo Asset Management version 7.6.1 configuration program, and then click **Finish**.

What to do next

Use the Maximo Asset Management version 7.6.1 configuration program to prepare WebSphere Application Server Network Deployment for Maximo Asset Management version 7.6.1 configuration.

Preparing WebSphere Application Server Network Deployment and configuring application server cluster profiles using the Maximo Asset Management configuration program

You can use the Maximo Asset Management version 7.6.1 configuration program to prepare WebSphere Application Server Network Deployment v8.5 for Maximo Asset Management configuration and configure application server cluster profiles.

About this task

When you configure Maximo Asset Management for a cluster environment, you must first prepare the WebSphere Application Server Network Deployment server and configure application server cluster profiles. You then configure Maximo Asset Management to work with the defined clusters.

You must define and configure clusters on the WebSphere Application Server Network Deployment deployment manager. If you want the cluster configuration to include members on other WebSphere Application Server Network Deployment nodes, you must log onto the server and run the Maximo Asset Management configuration program to configure a WebSphere Application Server Network Deployment profile and node to host those cluster members.

For performance reasons, you are encouraged to define a minimum of four clusters, each of which hosts a single product function. You can create additional

clusters based on your needs. Refer to the Best Practices for System Performance guide for detailed performance information.

Procedure

1. Log on to the system hosting the WebSphere Application Server Network Deployment deployment manager server.
2. Start the Maximo Asset Management configuration program from the Maximo Asset Management launchpad. In the launchpad navigation pane, click **Configure Product** and then click **Launch the Tivoli's Process Automation Suite configuration program**.
3. In the IBM Maximo Asset Management version 7.6.1 configuration operations page, click **Prepare WebSphere Application Server for configuration**.
4. In the Configure WebSphere Application Server panel, specify the installation location and configuration information for WebSphere Application Server Network Deployment and associated components. Select the options to configure the system for clusters and to automate the configuration of IBM HTTP Server.
5. In the **Configure Application Server Cluster Profiles** panel, specify information to use to create WebSphere Application Server Network Deployment deployment manager and application server profiles.
 - a. Select **Configure a new Deployment Manager at this server**.
 - b. Specify the profile name, node name, cell name, and SOAP port for the deployment manager profile.
 - c. Optional: Click **Advanced** to access the **Deployment Manager Profile Advanced Options** page where you can assign custom port values used by the deployment manager profile.
 - d. Specify the WebSphere Application Server Network Deployment administrator user credentials.
 - e. Click **New cluster** to create a new cluster. Specify a name and assign a single product function to the cluster.
 - f. Click **New Managed Node** to create a managed node. Specify a node name and a name for the profile that contains information about the new managed node. You can create more than one managed node, but you must have at least one managed node defined.
 - g. Select the managed node and click **New Server**.
 - h. From the **WebSphere Managed Node Server Definition** page, select **Web server**, and specify a name for the web server the managed node will use. Only one web server can be defined for a managed node.
 - i. Click **New Server**. From the **WebSphere Managed Node Server Definition** page, select **Application server cluster member**. Specify a name for the cluster member and select the cluster to associate with the cluster member. You can create as many cluster members as you need, but you must create at least one.
 - j. Repeat the process to create four clusters in total, and assign each a unique product function.
6. Specify additional configuration information in the Configure Application Server Advanced Options panel, if required.
7. If you chose to use a directory server for WebSphere Application Server Network Deployment administrative security, specify information about the directory server host, credentials and directory structure from the Configure Administrative Security panel.

8. In the Apply Deployment Operations panel select all deployment operation options, and then click **Finish**.

Results

WebSphere Application Server Network Deployment v8.5 is ready for Maximo Asset Management.

Related information:



<https://www.ibm.com/developerworks/community/files/form/anonymous/api/library/75dbdf46-1a08-429c-9742-bd340d7d1fd3/document/c51d5f5b-dea3-4043-a81f-d5213fc10063/media/Best%20Practices%20for%20System%20Performance%207.5.x.pdf>

Configuring cluster members on additional WebSphere Application Server Network Deployment nodes

You can use the Maximo Asset Management version 7.6.1 configuration program to configure cluster members on additional WebSphere nodes.

About this task

After you have defined clusters on the WebSphere Application Server Network Deployment deployment manager, you can configure cluster members on additional WebSphere Application Server Network Deployment nodes.

Procedure

1. Log on to the system serving as the WebSphere Application Server Network Deployment nodes.
2. Start the Maximo Asset Management configuration program from the Maximo Asset Management launchpad. In the launchpad navigation pane, click **Configure Product** and then click **Launch the Tivoli's Process Automation Suite configuration program**.
3. In the IBM Maximo Asset Management version 7.6.1 configuration operations page, click **Configure WebSphere Application Server Network Deployment for a new deployment**.
4. In the Configure WebSphere Application Server panel, specify the installation location and configuration information for WebSphere Application Server Network Deployment and associated components. Select the options to configure the system for clusters and to automate the configuration of IBM HTTP Server.
5. In the **Configure Application Server Cluster Profiles** panel, specify information to use to create additional cluster members on this nodes.
 - a. Select **Use an existing Deployment Manager**.
 - b. Specify connection information for the remote WebSphere Application Server Network Deployment deployment manager system.
 - c. Specify the WebSphere Application Server Network Deployment administrator user credentials.
 - d. Click **Load clusters** to load cluster information from the remote WebSphere Application Server Network Deployment deployment manager.
 - e. Click **New Managed Node** to create a managed node. Specify a node name and a name for the profile that contains information about the new managed node. You can create more than one managed node, but you must have at least one managed node defined.

- f. Select the managed node and click **New Server**.
 - g. From the **WebSphere Managed Node Server Definition** page, select **Application server cluster member**. Specify a name for the cluster member and select the cluster to associate with the cluster member. You can create as many cluster members as you need, but you must create at least one. You cannot create a new web server for the cluster because it was defined when the cluster was created on the remote WebSphere Application Server Network Deployment deployment manager.
 - h. Repeat the process to create new cluster members and assign them to clusters defined on the remote WebSphere Application Server Network Deployment deployment manager.
6. Specify additional configuration information in the Configure Application Server Advanced Options panel, if required.
 7. In the Apply Deployment Operations panel select all deployment operation options, and then click **Finish**.

Running the Maximo Asset Management 7.6.1 installation program

Use the Maximo Asset Management version 7.6.1 installation program to install Maximo Asset Management version 7.6.1.

Before you begin

Maximo Asset Management version 7.6.1 must be installed in a separate location on the administration workstation to any existing Maximo Asset Management versions.

About this task

In order to install Maximo Asset Management version 7.6.1, run the Maximo Asset Management version 7.6.1 installation program on the Maximo Asset Management administrative system.

Procedure

1. Log in to the Maximo Asset Management administrative workstation. If you run the IBM Maximo Asset Management version 7.6.1 installation program from a Linux or UNIX terminal window, you must be logged in as the root user.
2. Start the Maximo Asset Management launchpad.

Option	Description
Windows	<code>launchpad64.exe</code>
Linux or UNIX	<code>./launchpad.sh</code>

- a. Select a language for the installation session and click **OK**.
 - b. In the launchpad navigation pane, click **Install IBM Maximo Asset Management**.
 - c. From the **Install IBM Maximo Asset Management** panel, select **IBM Maximo Asset Management v7.6.1** and then click **Install**.
3. In the package selection panel, click **Next**.
 4. In the package prerequisite validation panel, review the results of the prerequisite check, and then click **Next**. If any errors are reported on this panel, resolve the issue and then click **Recheck Status** before continuing.

5. In the license agreement panel, review the license information for each package being installed, select **I accept the terms in the license agreements** if you agree with the terms, and then click **Next**.
6. In the Installation Manager installation location panel, specify path information for the shared resources directory and the Installation Manager installation directory, and then click **Next**. Installation Manager is the installation framework that is used to install Maximo Asset Management version 7.6.1 components. The shared resources directory is a common workspace directory used by Installation Manager when installing packages.
7. In the package installation location panel, select the IBM Tivoli's process automation suite package group, specify the path information for the Maximo Asset Management version 7.6.1 installation directory, and then click **Next**.
8. In the package summary panel, review the information for the planned installation, and then click **Install**. If you install in a non-English environment, you might notice the environment summary is listed as English. You configure supported languages for Maximo Asset Management later with the Maximo Asset Management configuration program.
9. After the installation is complete, select the option to start the Maximo Asset Management version 7.6.1 configuration program, and then click **Finish**. The Maximo Asset Management version 7.6.1 installation program exits and the Maximo Asset Management version 7.6.1 configuration program is started automatically.

What to do next

Use the Maximo Asset Management version 7.6.1 configuration program to configure Maximo Asset Management version 7.6.1.

Configuring Maximo Asset Management in a cluster environment using the Maximo Asset Management configuration program

You can use the Maximo Asset Management configuration program to configure Maximo Asset Management in a cluster environment after WebSphere Application Server Network Deployment has been configured for clustering.

Procedure

1. If the Maximo Asset Management version 7.6.1 configuration program is not open, start it from the Maximo Asset Management launchpad. In the launchpad navigation pane, click **Configure Product**, specify Maximo Asset Management installation location, and then click **Launch the Tivoli's Process Automation Suite configuration program**.
2. In the IBM Maximo Asset Management configuration operations page, click **Configure a New Deployment**.
3. In the Define Deployment Environment panel, specify information about Db2 and WebSphere Application Server Network Deployment servers you installed and prepared. Select the **Create and configure the database**, the **Complete configuration of WebSphere for your product**, and the **Deploy the product into a clustered environment** options to automatically configure WebSphere Application Server Network Deployment and Db2. After you define your deployment environment, click **Finish**.
4. In the Configure General Product Information panel, review summary details about the product components you are installing. Specify the appearance and

navigation features for your product, add an e-mail address to receive workflow messages, and choose whether or not to deploy sample data.

5. In the Configure the DB2 Instance panel, specify information about the Db2 instance to create for Maximo Asset Management.
6. In the Configure the DB2 Database panel, specify information about the Db2 database to create for Maximo Asset Management.
7. In the Configure the Application Server panel, specify information for the WebSphere Application Server Network Deployment domain manager where the clusters were defined, and then click **Load cluster information**.
8. Create an application for a function managed by a cluster, configure JMS for the application, and configure the Maximo Asset Management help application. You must create at least one application for each function in a cluster.
 - a. Click **Add application**.
 - b. Specify a name for the application and select the cluster name and web server associated with the function.
 - c. Optional: Change the function associated with the selected cluster.
 - d. Enable and configure JMS message handling for the application. The Maximo Integration Framework function requires JMS. The Reporting function does not support JMS. If you do not choose to use DB2 to store JMS data, a derby database is created to store the information.
9. Configure the Maximo Asset Management help application by supplying a name for the help application, selecting a cluster to assign it to, and selecting the web server to use for the application.
10. In the Configure Application Security panel, choose a security model for Maximo Asset Management. If you choose a security model that includes a directory server, specify information about the directory for the virtual member manager. Enter the user names and passwords for users that must be created for Maximo Asset Management. Do not use the user name as a password value.
11. Select languages.
12. In the Apply Deployment Operations panel, specify user interface preferences, select all available deployment operations, and then click **Finish**.

Chapter 7. Silent installation

The Maximo Asset Management silent installation option interacts with the Maximo Asset Management installation program by using a command prompt and a response file.

You must install the Installation Manager software before you can silently install the Maximo Asset Management or related middleware packages

Creating silent response files for installation

A response file records selections that you make and values that you provide when using the Maximo Asset Management installation program. The Maximo Asset Management installation program can then be run silently using the response file for input.

Before you begin

You can create a silent installation response file by setting the **record** environment variable, and then starting the installation program through the Maximo Asset Management launchpad. The response file is generated in the home directory of the user that started the program. You can determine the home directory of the current user the command appropriate for your operating system by using the following commands.

Windows

```
set HOMEPATH
```

UNIX

```
echo $HOME
```

The name of the file is `tpaeInstallerRspdate_and_time_stamp.xml`, for example, `tpaeInstallerRsp20130716105258.xml`

Procedure

1. Open a command prompt and set the **record** environment variable.

Option	Description
Windows	set record=true
Linux or UNIX	export record=true

2. Start the Maximo Asset Management launchpad.

Option	Description
Windows	launchpad64.exe
Linux or UNIX	./launchpad.sh

3. Click **Install Product**.
4. Select the components that you want to install, and then click **Install** to start the Maximo Asset Management installation program.

5. Select the packages you want to install silently, and specifying the shared resources and installation directories. When you are satisfied with your installation choices, click **Install** to install the packages.
6. Click **Finish** to exit the Maximo Asset Management installation program.

Sample silent installation response files

Instead of using the `tpaeInstallerRspdate_and_time_stamp.xml` file, you can use a sample response file and modify it according to your needs.

Sample files

Sample response files are provided in the directory where you extracted the IBM Maximo Asset Management 7.6.1 launchpad. If you update the values that are used in the sample response files, limit your updates to parameters such as installation locations, host names, port numbers, and user names. If you need to update non-environmental values, such as the main product name or the Installation Manager repository, create your own silent response file with the Installation Manager software.

Table 3. Samples of silent response files

File	Description
<code>launchpad_directory\SilentResponseFiles\Installer\Unix\ResponseFile_MAM_Install_Unix.xml</code>	Install Maximo Asset Management on Linux and UNIX.
<code>launchpad_directory\SilentResponseFiles\Installer\Unix\ResponseFile_MAM_Uninstall_Unix.xml</code>	Uninstall Maximo Asset Management on Linux and UNIX.
<code>launchpad_directory\SilentResponseFiles\Installer\Windows\ResponseFile_MAM_Install_Windows.xml</code>	Install Maximo Asset Management on Windows.
<code>launchpad_directory\SilentResponseFiles\Installer\Windows\ResponseFile_MAM_Uninstall_Windows.xml</code>	Uninstall Maximo Asset Management on Windows.
<code>launchpad_directory\SilentResponseFiles\Installer\Unix\ResponseFile_DB2_Install_Unix.xml</code>	Install IBM Db2 on Linux and UNIX.
<code>launchpad_directory\SilentResponseFiles\Installer\Windows\ResponseFile_DB2_Install_Windows.xml</code>	Install IBM Db2 on Windows.
<code>launchpad_directory\SilentResponseFiles\Installer\Unix\ResponseFile_DB2_Uninstall_Unix.xml</code>	Uninstall IBM Db2 on Linux and UNIX.
<code>launchpad_directory\SilentResponseFiles\Installer\Windows\ResponseFile_DB2_Uninstall_Windows.xml</code>	Uninstall IBM Db2 on Windows.
<code>launchpad_directory\SilentResponseFiles\Installer\Unix\ResponseFile_TPAE_WAS_Install_Unix.xml</code>	Install base components of WebSphere Application Server on Linux and UNIX.
<code>launchpad_directory\SilentResponseFiles\Installer\Windows\ResponseFile_TPAE_WAS_Install_Windows.xml</code>	Install base components of WebSphere Application Server on Windows.

Table 3. Samples of silent response files (continued)

File	Description
<code>launchpad_directory\SilentResponseFiles\Installer\Unix\ResponseFile_TPAE_WAS_Uninstall_Unix.xml</code>	Uninstall base components of WebSphere Application Server on Linux and UNIX.
<code>launchpad_directory\SilentResponseFiles\Installer\Windows\ResponseFile_TPAE_WAS_Uninstall_Windows.xml</code>	Uninstall base components of WebSphere Application Server on Windows.

Updating password values in silent response files

The Maximo Asset Management installation program requires the encryption of password values that are in the response files. If you need to update encrypted password values in a response file, use the Installation Manager string encryption utility.

About this task

The Installation Manager string encryption utility accepts a plain text password value and produces an encrypted version of that password. You must then copy and paste the encrypted value into the password field of the response file.

Procedure

1. Start the Installation Manager string encryption utility from the command line.

Option	Description
Windows	<code>c:\Program Files\IBM\InstallationManager\eclipse\tools\imutilsc newpasswordvalue</code>
AIX® or Linux	<code>/opt/IBM/InstallationManager/eclipse/tools/imutilsc encryptString newpasswordvalue</code>

Replace *newpasswordvalue* with your new plain text password value.

2. Copy the string in the **Encrypted version of the string** field.
3. Open the response file in a text editor, replace the password value with the copied encrypted password, and then save the file.

Silently installing the Installation Manager software

In order to install Maximo Asset Management and related middleware silently, the Installation Manager software must first be installed.

Procedure

1. Open a command prompt on the system and change to the directory where you unzipped the launchpad files.
2. Change directory to the folder that contains the installation manager program for your operating system, for example, `\Install\IM\installer.win64`.
3. Optional: Open the `silent-install.ini` file in a text editor and update default values.
4. Start the Installation Manager silent installation process.

Option	Description
Windows	installc -acceptLicense
Other operating systems	./installc -acceptLicense

Results

The Installation Manager software is successfully installed on the system. You can now proceed with silently installing Maximo Asset Management.

Silently installing Maximo Asset Management and related middleware

You can deploy Maximo Asset Management and associated middleware silently to perform an unattended installation based on predefined settings.

Before you begin

You must complete a successful installation to produce a response file that can be used to silently install Maximo Asset Management and related middleware. Alternatively, you can use one of the sample response files that are provided on the product media and modify the sample file.

If the response file was created on a different system, ensure that all values that are recorded in the response file are valid for the target system. Ensure that the path values that were defined when the response file was created are still valid for the target system. For example, you might need to update the **repository location** parameter values to indicate the correct path for product and middleware installation images.

If you are installing the product in a directory different from the path used during creation of the response file, update the **installLocation** parameter value. If you update the value for the **installLocation** parameter, you must also provide a new value for the **profile id** parameter.

Procedure

1. Copy the response file that you generated earlier and the Maximo Asset Management files to the target system.
2. Open a command prompt and change directory to the location of the Installation Manager program that is appropriate for your operating system, for example, `cd /opt/IBM/InstallationManager/eclipse/tools/`.
3. Silently start the Installation Manager program.

```
imcl -input responsefilename
-log logfile-name-acceptLicense
```

The **-input** parameter determines the response file to use, for example, `/SI/tpaeInstallerRsp20130716105258.xml`. The **-log** parameter determines where log files are written, for example, `/tmp/linuxDB2WASMAM_Log.xml`. You must include the full path when you specify the response and log files.

Results

The installation proceeds silently with the values that you provided in the response file. Using different response files as input, you can silently install middleware on separate systems. You can then use another response file to silently install Maximo

Asset Management on the system that is designated as the administrative workstation.

Silently uninstalling Maximo Asset Management and related middleware

You can silently uninstall Maximo Asset Management and associated middleware based on settings that were used during the installation.

Procedure

1. Open a command prompt and change to the *launchpad_home*\SilentResponseFiles\Installer directory, which contains the sample uninstallation response file.
2. Update the sample uninstallation response file with values that are used in your environment.
3. Silently start the Maximo Asset Management uninstallation program.

```
imcl -input responsefilename  
-log logfilename-acceptLicense
```

The default home directory for the **imcl** command is `c:\Program Files\IBM\Installation Manager\eclipse\tools\` on Windows systems and `/opt/IBM/InstallationManager/eclipse/` on Linux and UNIX systems.

The **-input** parameter determines the response file to use, for example, `C:\tmp\install_response.xml`.

The **-log** parameter determines where log files are written, for example, `C:\tmp\silent.log`.

You must include the full path when you specify the response and log files. The **-acceptLicense** parameter is used to accept the license automatically.
4. You can remove the Installation Manager software from the system using the uninstall program.

```
uninstallc
```

Table 4. Location of **uninstallc** command

Windows		Other operating systems
Admin		Admin
64-bit	C:\ProgramData\IBM\Installation Manager\uninstall	var/ibm/InstallationManager/uninstall
User		User
64-bit	C:\Users\User ID\AppData\Roaming\IBM\Installation Manager\uninstall	User Home/var/ibm/InstallationManager/uninstall

Chapter 8. Silent configuration

The silent configuration option allows you to interact with the Maximo Asset Management configuration program by using a command prompt and a response file.

The following tasks are required for silent configuration:

1. “Creating silent response files for middleware configuration”
2. “Creating a response file for silent Maximo Asset Management configuration” on page 82
3. “Silently configuring middleware” on page 83
4. “Silently configuring Maximo Asset Management” on page 83

Creating silent response files for middleware configuration

You create a response file by modifying one of the sample response files that is provided. The configuration program can then be run silently using the response file for input.

Procedure

1. Create a copy of the sample file, for example, `my-cfg-silent-win.properties`. Sample response files are in `launchpad_home\SilentResponseFiles\ConfigTool`.
2. Open the response file in a text editor, update values as required, and save the file.

Ensure that all values listed in the response file are valid for the target system, particularly path values. For example, you might need to update the **WAS.InstallLocation** parameter value to indicate the correct path for WebSphere Application Server Network Deployment relative to the target system.

If there are any Maximo Asset Management components you do not want to automatically configure, set the appropriate property value to false. For example, if you do not want to configure WebSphere Application Server Network Deployment on the system, set the **WAS.ND.AutomateConfig** value to false.

What to do next

After you have completed silent middleware configuration, you can proceed with silently configuring Maximo Asset Management.

Related tasks:

“Silently configuring middleware” on page 83

Middleware used with Maximo Asset Management can be configured silently by using a configuration response file.

Sample silent middleware configuration response files

Several sample response files are provided on the IBM Maximo Asset Management 7.6.1 product image. You can use a sample response file and modify it according to your needs.

Sample files

Silent response files are in the *launchpad_home\SilentResponseFiles\ConfigTool* directory of the product image.

Table 5. Samples of silent response files for middleware

File	Description
cfg-silent-aix.properties	Configure Maximo Asset Management middleware on AIX.
cfg-silent-linux.properties	Configure Maximo Asset Management middleware on Linux.

Creating a response file for silent Maximo Asset Management configuration

You create a response file by modifying one of the sample response files provided according to your needs. The configuration program can then be run silently using the response file for input.

Before you begin

There are several sample response files provided on the IBM Maximo Asset Management product image. The files are in the directory where you uncompressed the product image under the *<install_dir>/ConfigTool/samples* directory.

About this task

When you run the configuration program in silent mode, it uses the data in the response file to configure the product.

Procedure

1. Create a copy of the sample file and name it something appropriate, for example, *my-maximocfg-silent-win.properties*.
2. Open the response file in a text editor, update values as required, and save the file.

Ensure that all values listed in the response file are valid for the target system, particularly path values. For example, you might need to update the **WAS.InstallLocation** parameter value to indicate the correct path for WebSphere Application Server Network Deployment relative to the target system.

If there are any Maximo Asset Management components you do not want to automatically configure, set the appropriate property value to false. For example, if you do not want to configure WebSphere Application Server Network Deployment virtual member manager on the system, set the **WAS.VmmFullyAutomatedConfig** value to false.

Related tasks:

“Silently configuring Maximo Asset Management” on page 83
Maximo Asset Management can be configured silently by using an configuration response file.

Silently configuring middleware

Middleware used with Maximo Asset Management can be configured silently by using a configuration response file.

Procedure

1. Copy the response file you created earlier to the target system.
2. Open a command prompt and start the configuration program silently.

```
reconfigurePae  
-action deployMiddlewareConfiguration  
-inputFile responsefilename
```

The *responsefilename* parameter determines the response file to use, for example, C:\tmp\my-cfg-silent.properties. You must include the full path when you specify the response and log files.

Results

The configuration proceeds silently with the values that you provided in the response file.

What to do next

You can modify the silent configuration response file, copy it to another server, and perform further configuration. For example, you can use the configuration program to silently configure WebSphere Application Server Network Deployment on one server, and then modify the response file to configure IBM Security Directory Server on another server.

Silently configuring Maximo Asset Management

Maximo Asset Management can be configured silently by using an configuration response file.

Procedure

1. Copy the response file you created earlier to the target system.
2. Open a command prompt and start the Maximo Asset Management configuration program silently.

```
reconfigurePae  
-action deployConfiguration  
-inputFile responsefilename middlewarecomponents
```

The *responsefilename* parameter determines the response file to use, for example, C:\tmp\my-cfg-silent.properties. The *middlewarecomponents* parameter indicates which middleware component to configure, for example, -dbvendor DB2 or -j2eevendor WebSphere. In most cases, you configure middleware components together. You must include the full path when you specify the response files.

Results

The configuration proceeds silently with the values that you provided in the response file.

What to do next

You can modify the silent configuration response file, copy it to another server, and perform further configuration. For example, you can use the configuration program to silently configure WebSphere Application Server Network Deployment on one server, and then modify the response file to configure IBM Security Directory Server on another server.

Silently remove middleware configuration

You can use the same file you used to silently configure middleware to remove the configuration information.

About this task

Maximo Asset Management middleware configuration can be removed silently using the same configuration response file that was used to configure the product previously. You must edit the configuration response file that was used to configure the product previously before it can be used to remove configuration information from the product.

Procedure

1. Change to the directory containing the response file used to silently configure previously.
2. Make a copy of the response file and rename it. For example, rename the file to `my-uncfg-silent.properties`.
3. Open the file in a text editor and change the **MW.Operation** property value to **unconfigure**, and then save the file.
4. Open a command prompt and start the Maximo Asset Management unconfiguration program silently.

```
reconfigurePae  
-action deployMiddlewareConfiguration  
-inputFile responsefilename
```

The *responsefilename* parameter determines the response file to use, for example, `C:\tmp\my-uncfg-silent.properties`. You must include the full path when you specify the response file.

Remove product configuration silently

You can use the **removeConfiguration** action of the **reconfigurePae** command to remove Maximo Asset Management configuration information.

About this task

The **removeConfiguration** action is used to remove Maximo Asset Management configuration from the database and application server that was performed by the configuration tool. This action is equivalent to running the **removeJ2EEConfiguration** and **removeDatabaseConfiguration** actions together.

Procedure

1. Log on to the Maximo Asset Management administrative workstation.
2. Open a command prompt and change directory to `Install_Home\ConfigTool\scripts`.

3. Start the Maximo Asset Management configuration program silently.

```
reconfigurePae -action removeConfiguration  
-dbuser userid  
-dbpwd password  
-wasuser userid  
-waspwd password
```

The **-dbuser** and **-dbpwd** parameters are the user ID and password used to configure the database. The **-wasuser** and **-waspwd** parameters are the user ID and password used to configure IBM WebSphere Application Server Network Deployment.

Chapter 9. Configuring the HTTPOnly attribute

If applications do not start from the user interface in IBM WebSphere Application Server Network Deployment 8 environments, the problem can often be attributed to a security setting within IBM WebSphere Application Server Network Deployment. In particular, if the **HTTPOnly** attribute is set for session cookies, the applications are not accessible.

Procedure

1. Log on to the administrative console for IBM WebSphere Application Server Network Deployment.
2. From the navigation pane, browse to **Servers > Server Types > WebSphere application servers**.
3. Click the application server created for the product you want to update, for example, MXServer.
4. From the Configuration panel, under Container Settings, click **Session management**.
5. Under General properties, click **Enable cookies**. Do not clear this option. Click the label only.
6. Clear the **Set session cookies to HTTPOnly** check box to help prevent cross-site scripting attacks.
7. Click **OK**, save the changes, and then click **OK**.
8. Click **Save** and then click **OK**.
9. Navigate back to the Application servers table, and select the application server required.
10. Click **Restart** to restart the application server in order to apply the changes made.

Chapter 10. Installation and configuration programs log information

Log files generated by the Maximo Asset Management and configuration programs can provide details on completed and configuration tasks and any errors that might occur.

Maximo Asset Management installation and configuration programs log locations

Maximo Asset Management and associated middleware is installed through Installation Manager. The log files of Installation Manager are common to any installation, regardless of which components you choose to install. Log files for the Maximo Asset Management installation program are found on the system where it is run.

Table 6. Log file directories

Log file directory
C:\ProgramData\IBM\Installation Manager\logs
/var/ibm/InstallationManager/logs
C:\IBM\SMP\ConfigTool\logs
opt/IBM/SMP/ConfigTool/logs

In addition, if you receive an error credited to the J2EE server, examine the logs in the log directories for the deployment manager, node agent, and WebSphere Application Server application server.

When engaging IBM product support services, be prepared to provide these log files in an archive file. The LogZipper utility provided in the *install_home*\configtool\scripts directory can be used for this task. If you use the LogZipper utility, all relevant log files are archived in *install_home*/configtool/debug/YYYYMMDD_hhmmss.zip.

Chapter 11. Post installation tasks

There are several post installation tasks required in order to complete the Maximo Asset Management deployment.

Installing help locally

Product help for Maximo Asset Management is provided online in IBM Knowledge Center. If you want to install help locally, you can download IBM Knowledge Center and help packages from Fix Central.

Installing help

You can download help packages from Fix Central that contain the same documentation packages that are available online in IBM Knowledge Center. You add the help packages and configuration files to a local installation of IBM Knowledge Center

Procedure

1. To download a locally-installable version of IBM Knowledge Center and help packages from Fix Central, follow the instructions at <http://www-01.ibm.com/support/docview.wss?uid=swg24041962>.
2. Extract the IBM Knowledge Center package to the location where you want to install it. The default installation location is C:\KnowledgeCenter. If you install IBM Knowledge Center to a different location, you must update the path value in the *taxonomy.properties* file for each help package that you install.
3. Extract a help package to a temporary location. The extracted files include one or more plugin folders, a properties file and a taxonomy file.
4. Copy all com.ibm.prod.doc plugin folders from the help package to the *install_home/KnowledgeCenter/usr/content/KCXhtml* directory.
5. Copy the properties file to the configuration directory, for example to *install_home/KnowledgeCenter/usr/conf/SSLKT6_7.6.1.properties*.
6. Open the *taxonomy.properties* file in a text editor and update the path value, if necessary, to point to the installed location. For example, change the value of the Path property from C:/KnowledgeCenter/usr/content/KCXhtml to E:/IBM/SMP/KnowledgeCenter/usr/content/KCXhtml, where IBM Knowledge Center is installed at E:/IBM/SMP/KnowledgeCenter.
7. Replace the *install_home/KnowledgeCenter/usr/taxonomy/KC_taxonomy.ditamap* with the version of the KC_taxonomy.ditamap file that is included in the help package.
8. In the *install_home/KnowledgeCenter/bin* directory, click **startKC.bat** on Windows or **startKC.sh** on Linux or AIX to start IBM Knowledge Center.
9. In a browser, open http://install_home:port/kc to view the product help, for example <http://127.0.0.1:9090/kc>.
10. In Maximo Asset Management, redirect the application help links to point to your local installation of IBM Knowledge Center:
 - a. In the System Properties application, filter for mxe.help properties.
 - b. Change the mxe.help.host and mxe.help.port properties to the host and port values for your local installation of IBM Knowledge Center, such as the default host value of 127.0.0.1 and default port value of 9090.

- c. Change the `mxe.help.path` property value from `/support/knowledgecenter/` to `/kc/`.
 - d. Save the changes and click **Live Refresh** to update the values in the product database.
11. To stop IBM Knowledge Center, in the `install_home/KnowledgeCenter/bin` directory, click **stopKC.bat** on Windows or **stopKC.sh** on Linux or AIX.

IBM Knowledge Center configuration

IBM Knowledge Center requires minimal configuration to run help packages for IBM products in your local environment. You can also configure it to provide different content in separate instances of IBM Knowledge Center or to run existing Eclipse help plugins in IBM Knowledge Center.

Changing the IBM Knowledge Center URL

If you install IBM Knowledge Center on your local computer, when you start the server, the help is available in a browser at the default URL of `http://localhost:9090/kc`. The host value changes, depending on where you install IBM Knowledge Center. If the default port is already in use, you can change the port value in the `kc_ant.properties` file in the `etc` directory.

If you want to provide different help to different audiences or if you want to host help for product versions that are not compatible with each other, you can install multiple instances of IBM Knowledge Center on the same computer. You rename the additional instances to unique directory names, such as `KnowledgeCenter2` and `KnowledgeCenter3`, and you configure the `kc_ant.properties` file in the `etc` directory so that each instance runs on a different port.

Maintaining taxonomy files

Each product version in the IBM software catalog has a unique taxonomy value that forms part of the URL for the product help on `www.ibm.com`. For example, the taxonomy value for Maximo Asset Management, version 7.6.0.5, is `SSLKT6_7.6.0.5`, and the URL for the product welcome page is `http://www.ibm.com/support/knowledgecenter/SSLKT6_7.6.0.5/com.ibm.mam.doc/welcome.html`. The `taxonomy.properties` file and the `KC_taxonomy.ditamap` file control the taxonomy values in IBM Knowledge Center.

Each help package includes a `taxonomy.properties` file that is specific to the product version. You must add this file to the `usr/conf` directory in IBM Knowledge Center. If you add help packages for multiple products to IBM Knowledge Center, the `usr/conf` directory must contain a separate `taxonomy.properties` file for each help package.

The `KC_taxonomy.ditamap` file lists each product version in the IBM software catalog, and the file is frequently updated as new products and new versions of products are released. A basic version of the `KC_taxonomy.ditamap` file is provided as a placeholder in the `usr/taxonomy` directory in IBM Knowledge Center but it does not contain a comprehensive list of product taxonomy values. You must replace this placeholder file with the version of the `KC_taxonomy.ditamap` that is included in the help package.

When you add multiple help packages to IBM Knowledge Center, each help package includes a `KC_taxonomy.ditamap` file. Because of the dynamic nature of this file, the included `KC_taxonomy.ditamap` files might be at different versions. Always

use the most recent version of the file because taxonomy values are added to the file incrementally.

Troubleshooting

When you start IBM Knowledge Center after adding a new help package, index and cache files are created to enable faster search and retrieval of help topics. If the new help topics do not show in a browser, check if subdirectories were created for the product version in the runtime/diskcache and runtime/index directories. If these subdirectories were not created, check that the *taxonomy.properties* file exists in the usr/conf directory and that it contains the correct path to the main help plugin in the usr/content/KCXhtml directory. If the *taxonomy.properties* is in the correct location and contains the correct path to the help plugin, it is likely that you forgot to add the latest version of the KC_taxonomy.ditamap to the usr/taxonomy directory.

After troubleshooting, before you start IBM Knowledge Center, you can delete the product version subdirectories in the runtime/diskcache and runtime/index directories, to ensure that the content is fully refreshed.

Help components

Help components include a locally installable version of IBM Knowledge Center and help packages that contain content plug-ins for product versions. You can download a locally installable version of IBM Knowledge Center to deploy help packages in your local environment.

IBM Knowledge Center

A stand-alone help system that includes a WebSphere Application Server Liberty, version 8.5.5.x, embedded server. IBM Knowledge Center is distributed to Maximo customers on <https://www-933.ibm.com/support/fixcentral/>. IBM Knowledge Center is available for Windows, Linux, or AIX operating systems and you can run IBM Knowledge Center on a local computer, server, or read-only media.

After you extract the IBM Knowledge Center package, you add product help packages to it to deploy help in your local environment. You can use IBM Knowledge Center to host help packages for several products at the same time, if the products are on compatible release versions. If you want to host help packages that are not compatible with one another, you can run more instances of IBM Knowledge Center that you configure to run on different ports.

Help packages

Contain the same documentation that is available on <http://www.ibm.com/support/knowledgecenter> and include one or more content plug-ins. Help packages also include the following files that are required by IBM Knowledge Center:

- A *taxonomy.properties* file contains the taxonomy value for the product version and the path to the main *toc.ditamap* file for the plug-in or plug-ins in the help package.
- The KC_taxonomy.ditamap file lists the taxonomy values for all products in the IBM software catalog. A basic version of this file is included in IBM Knowledge Center but this version of the file is not up-to-date. The KC_taxonomy.ditamap file that is included in the help package is the current version of the file when the help package is created.

Help packages include instructions for where to add the plug-ins and the additional files to IBM Knowledge Center.

IBM Knowledge Center versions

The locally installable versions of IBM Knowledge Center are based on IBM Knowledge Center, version 1.5. This version has a different appearance to IBM Knowledge Center, version 2.0, which is on <http://www.ibm.com/support/knowledgecenter>. The functions are similar but some differences in navigation and search exist. PDF creation is not supported on the locally installable version.

When a locally installable IBM Knowledge Center, version 2.0, is available, it will be distributed to customers who want to update their local version.

Maximo Asset Management documentation library

The help packages in the documentation library mirror the product catalog and installation environment. Either the Maximo Asset Management help package or the Maximo Asset Management Multitenancy help package must be installed in the same IBM Knowledge Center environment where you install help packages for industry solutions and add-on products.

The Maximo Asset Management and Maximo Asset Management Multitenancy help packages contain multiple plugins. Most industry solution and add-on help packages contain just one plugin but some contain multiple plugins. When a help package contains multiple plugins, one plugin acts as the navigation plugin and contains the main *toc.ditamap* file that controls the table of contents for all plugins in the help package. In IBM Knowledge Center, the *taxonomy.properties* file in the help package specifies the path to the main *toc.ditamap* file in the navigation plugin.

Maximo Asset Management help package

This help package includes the following plugins:

com.ibm.mam.doc

Navigation plugin that manages the table of contents and sets the product taxonomy values for all plugins in the help package. Content includes the welcome page and product overview, planning, getting started, and managing financial processes topics.

com.ibm.mam.inswas.doc

Help for installing Maximo Asset Management on WebSphere Application Server.

com.ibm.mam.inswl.doc

Help for installing Maximo Asset Management on Oracle WebLogic Server.

com.ibm.mbs.doc

Help for administering Maximo Asset Management, application design, workflow design, working with Migration Manager, implementing high availability, and using applications. This plugin is a content reuse plugin that provides topics for use by other plugins but does not have a table of contents or a taxonomy value of its own. The content is used extensively by most help packages and you must include this plugin in IBM Knowledge Center to ensure that content is coherent and that links resolve for all help packages.

com.ibm.mif.doc

Help for integrating Maximo Asset Management data with external

applications. Similar to `com.ibm.mbs.doc`, this plugin is a content reuse plugin and must be included in IBM Knowledge Center.

`com.ibm.support.mbs.doc`

Troubleshooting and support information for Maximo Asset Management and for industry solutions and add-on products. Industry solution and add-on product troubleshooting topics are managed conditionally and are visible only if that help plugin is also available in IBM Knowledge Center.

Maximo Asset Management Multitenancy help package

This help package contains a subset of the plugins in the Maximo Asset Management help package and the content is specifically aimed at tenants in a multitenancy environment. You cannot install Maximo Asset Management plugins and Maximo Asset Management Multitenancy plugins in the same instance of IBM Knowledge Center environment. If you want to support both libraries, you must configure separate instances of IBM Knowledge Center to support them.

This help package includes the following plugins:

`com.ibm.mt.doc`

Navigation plugin that manages the table of contents and sets the product taxonomy values for all plugins in the help package. Content includes the welcome page and product overview, planning, getting started, and managing financial processes topics. Content also includes topics that are specific to a tenant in a multitenancy environment.

`com.ibm.mbs.doc`

Content reuse plugin and content is filtered to exclude information that is not relevant to tenants in a multitenancy environment.

`com.ibm.mif.doc`

Content reuse plugin and content is filtered to exclude information that is not relevant to tenants in a multitenancy environment.

Industry solution and add-on help packages

Most industry solution and add-on help packages contain just one plugin, but some contain multiple plugins. If there are multiple plugins in a help package, one plugin acts as the navigation plugin and controls the table of contents for all of the plugins in the help package. You must ensure that you add all of the plugins that are included in a help package to IBM Knowledge Center so that links resolve and content is complete.

The help packages for industry solutions and add-on products are designed to be used with the associated version of the Maximo Asset Management help package. You can check which version of Maximo Asset Management or Maximo Asset Management is a prerequisite for an industry solution or add-on product version at <https://www.ibm.com/developerworks/community/wikis/home?lang=en#!/wiki/IBM%20Maximo%20Asset%20Management/page/Other%20Maximo%20products%20system%20requirements>. You can install non-recommended versions of help packages together but some links might not resolve or some of the functionality described in topics might not be available to users.

Configuring initial data

After you successfully install and configure Maximo Asset Management components, you must complete several data configuration tasks before you use Maximo Asset Management.

Before you begin

- Create security groups and add users to the security groups.
- If you are using a directory server as part of your deployment, ensure that the user names are created in your LDAP repository.
- To ensure that you have the accounting information that you need, consult the Financial department of your organization.

Procedure

1. Log in to Maximo Asset Management by entering the user name `maxadmin` and the password that you specified during the installation.
2. If you didn't set the SMTP server by using the Configuration tool, configure the SMTP server to send users email notifications of system events. To learn about the range of system properties in Maximo Asset Management, see the System properties information.
 - a. From the **Go To** menu, select **System Configuration > Platform Configuration > System Properties**.
 - b. In the Global Properties table window, use the filter feature to search for and expand the `mail.smtp.host` property.
 - c. In the **Global Value** field, specify the SMTP host name.
 - d. Select the `mail.smtp.host` check box.
 - e. From the **Common Actions** menu, click **Live Refresh**.
 - f. In the Live Refresh window, click **OK**.
 - g. In the Global Properties table window, use the filter feature to search for the `mx.adminEmail` property.
 - h. Expand the `mx.adminEmail` property and in the **Global Value** field, specify your email address.
 - i. Select the `mx.adminEmail` record check box.
 - j. From the **Common Actions** menu, click **Live Refresh**.
 - k. In the Live Refresh window, click **OK**.
3. Define a currency code.
 - a. From the **Go To** menu, select **Financial > Currency Codes**
 - b. Click **New Row** and specify a currency code and a description. For example, enter USD for United States of America Dollar.
 - c. Click **Save Currency**.
4. Define item sets and company sets.
 - a. From the **Go To** menu, select **Administration > Sets**.
 - b. Click **New Row**.
 - c. Specify an item set name. For example, enter IT Items.
 - d. In the **Type** field, specify ITEM.
 - e. Click **New Row**.
 - f. Specify a company set name. For example, enter IT Comps.
 - g. In the **Type** field, specify COMPANY.
 - h. Click **Save Sets**.

5. Create an organization.
 - a. From the **Go To** menu, select **Administration > Organizations**.
 - b. From the toolbar, click **New Organization**.
 - c. Specify an organization name. For example, enter EAGLENA, and enter a long description.
 - d. Specify the base currency that you defined in step 3.
 - e. Specify the item set and the company set that you defined in step 4.
 - f. In the **Default Item Status** field, set the status to PENDING.
 - g. Click the **Sites** tab and select **New Row** under the Sites table window.
 - h. Specify a site name. For example, enter Factory01 and enter a long description.
 - i. Click **Save Organization**.
6. Create a general ledger account component.
 - a. From the **Go To** menu, select **System Configuration > Platform Configuration > Database Configuration**.
 - b. From the **More Actions** menu, select **GL Account Configuration**.
 - c. Click **New Row**.
 - d. Specify a component name. For example, enter MYCOMPONENT.
 - e. Specify a length for the component. For example, enter 5.
 - f. Specify a type for the component. For example, select Alphanumeric.
 - g. Click **OK**.
7. Apply changes to the database.
 - a. From the **More Actions** menu, select **Manage Admin Mode**.
 - b. Select **Turn Admin Mode ON** and click **OK**. This task takes several minutes to complete. You can click **Refresh Status** to view the progress.
 - c. From the **More Actions** menu, select **Apply Configuration Changes**. Ensure that the status To Be Changed does not appear in the status column of the listed objects.
 - d. From the **More Actions** menu, select **Manage Admin Mode**.
 - e. Select **Turn Admin Mode OFF** and click **OK**. If you do not turn off Admin Mode, cron tasks fail.
8. Create a general ledger account.
 - a. From the **Go To** menu, select **Financial > Chart of Accounts**.
 - b. In the Organizations table window, select your organization.
 - c. From the **More Actions** menu, select **GL Component Maintenance**.
 - d. In the Components table window, select the component that you entered in step 6 and click **New Row**.
 - e. Specify a GL Component value and a description, and then click **OK**.
 - f. In the GL Accounts table window, click **New Row**.
 - g. Specify a General Ledger Account and click **Save GL Account**.
 - h. From the **Go To** menu, select **Administration > Organizations**.
 - i. Find your organization and select the record.
 - j. In the **Clearing Account** field, specify the general ledger account that you created.
 - k. Select **Active**.
 - l. Click **Save Organization**.
9. Authorize a security group to modify a general ledger component type.

- a. From the **Go To** menu, select **Security > Security Groups**.
 - b. Select the group that provides authorization. For example, select **FINANCE**.
 - c. Click the **GL Components** tab.
 - d. For each GL Component that is listed, select the **Authorized** check box. As a shortcut, you can select **Authorize Group to Change All GL Component Types**.
 - e. Click **Save Group**.
10. Update the company-related accounts.
- a. From the **Go To** menu, select **Financials > Chart of Accounts**.
 - b. Select your organization and from the **More Actions** menu, select **Company-Related Accounts**.
 - c. Click **New Row** and specify the company type **Courier**.
 - d. Enter an account number in the **RBNi Account**, **AP Suspense Account**, and **AP Control Account** fields. You can specify the same account number in each field.
 - e. Click **OK**.
 - f. From the **More Actions** menu, select **Update Database** and click **OK**.
11. Create a default insert site.
- a. From the **Go To** menu, select **Security > Users**.
 - b. Find **maxadmin** and select the record.
 - c. In the **Default Insert Site** field, specify the site name that you created in step 5.
 - d. In the **Storeroom Site for Self-Service Requisitions** field, specify the same site name.
 - e. Click **Save User**.
12. Define work types. Work types denote the importance of the work task.
- a. From the **Go To** menu, select **Administration > Organizations**.
 - b. Find your organization and select the record.
 - c. From the **More Actions** menu, select **Work Order Options > Work Type**.
 - d. Click **New Row**.
 - e. In the **Work Order Class** field, select **WORKORDER**.
 - f. Specify a **Work Type**. For example, enter **MAJOR**.
 - g. Set the **Start Status** to **In Progress**.
 - h. Set the **Complete Status** to **Completed**.
 - i. Click **New Row** and repeat steps f-i to create another work order class with a different work type. For example, enter **MINOR**.
 - j. Click **New Row** and repeat steps f-i to create a **CHANGE** work order class with a different work type. For example, enter **SIG** to represent a significant change.
 - k. Click **OK** and click **Save Organization**.

Related information:

Integrating data with external applications

System properties

Synchronizing users and groups

When you select application server security, the scheduled synchronization of users and groups that occurs between LDAP repositories and Maximo Asset Management is governed by the federated repositories.

Before you begin

View the cron task configuration information in the Administering section of the Knowledge Center.

About this task

LDAP repositories managed by IBM WebSphere Application Server Network Deployment through Virtual Member Manager are synchronized through the VMMSYNC cron task.

To configure the synchronization schedule between LDAP repositories and Maximo Asset Management, complete the following steps:

Procedure

1. Open a web browser and point to `http://host name:port/maximo`.
2. Log in to Maximo Asset Management using the maxadmin user ID.
3. From the Maximo Asset Management interface, navigate to **Go To > System Configuration > Platform Configuration > Cron Task Setup**.
4. Search for the appropriate cron task in the **Cron Task** field and configure it.
5. Set the task to **active**.

What to do next

By default, the cron task performs its task every 5 minutes. Change the **Schedule** field of the cron task if you want to change the interval.

Adding sample data to the Maximo Asset Management database post configuration

Using the **maxinst** command, you can add sample data to the Maximo Asset Management database after the initial installation and configuration of Maximo Asset Management.

Before you begin

The **maxinst** command does not provide default values for table space parameters. You must specify the data table space name and the index table space name that you specified during the installation. The **maxinst** command replaces the current database schema and data. Do not add sample data to the Maximo Asset Management database if you want to preserve records that are currently stored in the database. Running the **maxinst** command removes all post deployment configuration information and data in the Maximo Asset Management database.

About this task

If you created a database either automatically or manually during the installation, you can use the **maxinst** command to create a sample data in that database

instance. You can add sample data to the database by selecting the option on the initial configuration panels or using the following steps:

Procedure

1. Back up the existing database.
2. Unzip the *install_home\IBM\SMP\Maximo\tools\maximo\en\maxdemo.dbtype.zip* file. Replace the *dbtype* variable with the extension that is appropriate for the type of database you used for the Maximo Asset Management deployment. Available options are ora, sqs, or db2.
3. Change the *install_home\IBM\SMP\Maximo\tools\maximo\en\maxdemo.dbtype* file to the name of the Maximo Asset Management database you configured during the initial deployment. For example, rename the file to max76db.db2
4. Open a command prompt and change to the *install_home\IBM\SMP\Maximo\tools\maximo* directory.
5. Populate the database with sample data. You must specify the table space name parameters when you run the **maxinst** command.
 maxinst -stablespace -ttablespace -imax76db For example, for Oracle Database or for Db2, enter maxinst -sMAXDATA -tMAXDATA -imax76db. For SQL Server, enter maxinst -tPRIMARY -sPRIMARY -imax76db. The system reads the maximo.properties file for database connectivity information. The maximo.properties file is in the *install_home\IBM\SMP\Maximo\Applications\Maximo\Properties* directory.
6. Populate the database by running commands with specific parameter values. Use the following **maxinst** database parameters:

Parameter	Description
-a	Database alias. If not specified, the alias mxe.db.url.property is used.
-d	Log file directory. If you are using the -l parameter, the log file is sent to the specified directory. Otherwise, the log file is sent to the log directory, for example <i>install_home\IBM\SMP\Maximo\tools\maximo\logs</i> .
-e	Runs the SQL. This parameter is required and already present in the maxinst.bat file.
-f	File name for the properties file. If not specified, maximo.properties is used.
-i	File name of the input file (without path or extension).
-k	Directory of the properties file.
-l	Creates a detailed log file. This parameter is already present in the maxinst.bat file.
-m2	Optional value for SQL Server: Multiplies the column width for strings by 2. This value is required for double-byte character sets.
-o	If you are using the -l parameter, the -o parameter specifies the file name for the log file.

Parameter	Description
-p	Password for the database connection. If not specified, the <code>mxe.db.password</code> property or MAXIMO is used. If MAXIMO is used, it must be entered in uppercase letters.
-s	Required value: Table space for index storage.
-t	Required value: Table space for table storage.
-u	User name for database connection. If not specified, the <code>mxe.db.user</code> property or MAXIMO is used. If MAXIMO is used, it must be entered in uppercase letters.
-x	Required value for UNIX: Fixes the doclink file separators in UNIX environments. Note: If a UNIX environment is deployed without using this parameter, the attached documents do not function properly.
-y	Multiplies the column width for strings by 2. This value is required for double-byte character sets.

- From the *install_home\IBM\SMP\ETC* directory, open the `install.properties` file and specify the installation-related properties. You can add these properties to the database from the System Properties application.

Results

The Maximo Asset Management database is populated with sample data.

If an error occurs when you run the **maxinst** command, check the log file in the *install_home\IBM\SMP\Maximo\tools\maximo\logs* directory. If the **maxinst** command fails, you must correct the error and rerun the **maxinst** command to complete the Maximo database schema deployment before you can start the application.

Chapter 12. Maintaining EAR files

This section contains information about maintaining Maximo Asset Management EAR files.

The following instructions are used to manually build or uninstall the Maximo Asset Management `maximo.ear` file on WebSphere Application Server Network Deployment.

Although the Maximo Asset Management installation program deploys these EAR files when you install, there might be a few instances where it would be desirable to rebuild these EAR files manually:

- If you modify any database connection parameters in the `maximo.properties` file after the initial installation, you must rebuild of the `maximo.ear` file, and then redeploy it in WebSphere Application Server Network Deployment. In this scenario, you would likely only rebuild and redeploy the `maximo.ear` file.
- Maximo Asset Management must be installed into a WebSphere Application Server Network Deployment application server. However, Maximo Asset Management can be run within the framework of a WebSphere Application Server Network Deployment cluster. If you want to deploy Maximo Asset Management in a cluster, you can either redeploy the Maximo Asset Management EAR files into a cluster, or, create a cluster from the application server used during the install. If you have already installed Maximo Asset Management into an application server but would like to redeploy into a cluster, then you must either uninstall the MAXIMO application (“Manually uninstalling applications from WebSphere Application Server Network Deployment” on page 104), or provide a new name for the application when installing the MAXIMO application into a cluster (“Manually installing applications in WebSphere Application Server Network Deployment” on page 104).
- If you have installed Maximo Asset Management into a development environment, you might at some point like to migrate the deployment into a test or production environment. In this scenario, you must deploy both the `maximo` and `maximo help` applications into the new environment.

The steps outlined in “Manually installing applications in WebSphere Application Server Network Deployment” on page 104 should be performed for both applications.

Building EAR files

You can manually build Maximo Asset Management EAR files if, for example, you modify a database connection parameter in the `maximo.properties` file after the initial installation.

About this task

To manually build Maximo Asset Management EAR files, use the `buildmaximoeear` command.

Windows

```
install_home\maximo\deployment\buildmaximoeear.cmd
```

Linux and UNIX

```
install_home/maximo/deployment/buildmaximoeear.sh
```

Manually deploying Work Center WAR files

The Work Center WAR file, `maximo-x.war`, is automatically built and deployed during the installation and configuration process. However, you can manually build the Work Center WAR file by using the **buildmaximo-xwar** command.

Procedure

1. Log on to the administrative workstation, open a command line, and change to the `maximo-root\deployment` directory.
2. Run the **buildmaximo-xwar** command. The `maximo-x.war` file is created in `maximo-root\deployment\default` directory.
3. Deploy the `maximo-x.war` file on the Maximo Asset Management application server.

Configuration	Action
Simple	Deploy the <code>maximo-x.war</code> file on the Maximo Asset Management application server or UI cluster.
Proxy server that communicates with Maximo Asset Management by using a single hostname and port	Deploy the <code>maximo-x.war</code> file on a separate application server.
Cross origin requests to the Maximo Asset Management server.	Configure the CORS settings by using servlet filters that set access control headers on the application server that hosts the <code>maximo-x</code> application.

Results

After you build and deploy the `maximo-x.war` file, use the default context path `/maximo-x` to access the Work Centers.

Manually uninstalling applications from WebSphere Application Server Network Deployment

This section contains information about uninstalling Maximo Asset Management applications from WebSphere Application Server Network Deployment.

Procedure

1. Log in to the WebSphere Application Server Network Deployment administrative console, select **Servers > Server Types > WebSphere application servers**, select `MXServer` and click **Stop**.
2. Click the Applications link.
3. Select the check box next to the application you are uninstalling. By default, the Maximo Asset Management applications are named `maximo` and `maximoiehs`.
4. Click **Uninstall**.

Manually installing applications in WebSphere Application Server Network Deployment

Maximo Asset Management applications can be added to WebSphere Application Server Network Deployment.

Procedure

1. Log on to the WebSphere Application Server Network Deployment administrative console.
2. Browse to **Applications > New Application > New Enterprise Application**.
3. From the Specify the EAR, WAR, JAR, or SAR module to upload and install page, select **Local file system**.
4. Browse to the location on your system of the maximo.ear file and click **Next**.
5. Select **Detailed** and then click **Next**.
6. From the Application Security Warnings panel, click **Continue**.
7. Click **Step 2: Map modules to servers**.
8. Highlight all entries listed in the Clusters and servers field, check all check boxes for Modules listed in the table, and click **Apply**.
9. Click **Step 11: Map virtual hosts for Web modules**.
10. Check all check boxes for web modules listed in the table.
11. Expand **Apply Multiple Mappings**.
12. Select a virtual host, for example, maximo_host, from the Virtual Host menu, and click **Apply**.

Figure 13. Map virtual hosts for Web modules

Step 11: Map virtual hosts for Web modules

Specify the virtual host for the Web modules that are contained in your application. You can map all modules to the same virtual host or disperse them among several hosts.

☒ **Apply Multiple Mappings**

To apply multiple mappings, follow the steps below.

1. Select one or more check boxes in the table.
2. Complete mappings and click the "Apply" button.

Virtual Host: maximo_host Apply

Select	Web module	Virtual host
☐	MAXIMO Web Application	maximo_host
☐	MBO Web Application	maximo_host
☐	MEA Web Application	maximo_host
☐	REST Web Application	maximo_host

13. Click **Step 15: Map security roles to users or groups**.
14. Select the check box for maximouser in the Role table, and then select **Everyone** from the Map Special Subjects menu.
15. Click **Step 17: Summary**, review the summary information, and click **Finish**.

Chapter 13. Command line configuration

Maximo Asset Management includes a configuration program, **reconfigurePae**, located in the *Install_Home \ConfigTool\scripts* directory, that is accessed from the command line. This command line configuration program performs the same duties as the Maximo Asset Management configuration program user interface. Command line configuration is used to quickly update configuration values when you choose to not use the configuration tool user interface.

When you install a fix pack or upgrade Maximo Asset Management, the configuration program uses values that are recorded from the previous deployment. These values are stored on the administrative system in the *install.properties* and *maximo.properties* files that are located under the *install_home\etc* and *install_home\maximo\applications\maximo\properties* directories.

If you make any environmental changes to any of the systems that are used for the original deployment, they must be recorded in the *install.properties* and *maximo.properties* files. Typically, these types of changes would include changing a host name or updating a password, for example.

You can update these values manually, or you can use the configuration command line interface tool to update configuration values for your existing deployment when they change. Properties that are specified for the configuration command line interface tool, either as parameters, or in an input properties file, replace existing properties in the *maximo.properties* and *install.properties* files. Properties are encrypted when they are saved.

You can complete the following tasks with the configuration command line interface tool:

- Change the security model for the original deployment. For example, you can migrate from Maximo Asset Management-based security to WebSphere Application Server security. This option is not available for Oracle WebLogic Server.
- Confirm that updated property values conform to required input domains. Validate credentials, host names, and available ports.
- Update database or application server configuration settings without the server available. These values cannot be validated in this scenario.
- Clone an existing environment and use the configuration command line interface tool to reconfigure the administrative workstation to use the new servers. The cloned environment must use the same directory structure as the original.
- Create an environment (non-cloned) and use the configuration command line interface tool to create all required artifacts database, table spaces, and application server objects, for example.
- Remove configuration from a previously configured database.

Configuration parameter validation

Use the Maximo Asset Management command line configuration program to validate input in the same way the Maximo Asset Management configuration program validates input in the user interface.

You can validate the following items with the Maximo Asset Management command line configuration program.

- Host names or IP addresses are correctly formatted and are reachable.
- User IDs and passwords meet length and character set criteria.
- Specified credentials are used to authenticate to WebSphere Application Server.
- Specified port values are listening on the corresponding host. Port values contain numbers only and are within a valid range.
- Middleware installation directories that are supplied exist.
- Preconfigured middleware can authenticate to the product database.
- Required objects such as JMS queues, SIB destinations, databases, and table spaces exist.
- Required WebSphere Application Server virtual member manager users exist.
- Sufficient authority is available to create WebSphere Application Server virtual member manager users.
- Remote login credentials are valid.
- There is enough space in the supplied directories to create database objects.

Input properties files

You can use property files as input for the Maximo Asset Management command-line configuration program.

The following sample input property files are provided with the Maximo Asset Management command-line configuration program.

- DB2_Sample_input.properties
- Oracle_Sample_input.properties
- SQLServer_Sample_input.properties
- WebSphere_App_Server_Sample_input.properties

These sample files are in the `ibm\smp\configtools\samples` directory. Each of these sample files contains properties that are associated with a specific database or application server type. They contain comments and properties you can update with values from your environment. You can then use the updated file as input for the configuration command line interface tool with the **-input** parameter.

All input properties, introduced from either the command line or in the input properties file, are validated before they are used. After validation is successful, the `maximo.properties` and `install.properties` files are updated with the values you provided.

Command line interface parameters

The following parameters can be used with the configuration command line program to configure your environment.

Table 7. Maximo Asset Management command line configuration program parameters

Parameter name	Description
-action	Configuration action. • addLanguages – Adds additional languages to a current deployment. • configureProducts - Configures more products after an initial installation and configuration. This action should be used to configure multiple products after they are installed and should also be used in an upgrade scenario. • configureProductsDBLite - Configures more products after an initial installation and configuration using the DB Lite feature. This action can configure multiple products after they are installed and can also be used in an upgrade scenario. • deployConfiguration - Configures initial installation. This action can configure multiple products after they are installed. This action is used for new installations only. • deployDatabaseConfiguration - Validates command input and defines configuration property values for a new database for the current product. • deployJ2eeConfiguration - Validates command input and defines configuration property values for a new application server for the current product. • deployMiddlewareConfiguration – Configures initial middleware installation. • disableAppSecurity - Disables application security for the application. Security is handled entirely through Maximo Asset Management. This action sets the mxe.useAppServerSecurity property to a value of 0. This value is written to the database when updated. • disableDB2TextSearch - Disable the full text search feature on a Db2 database. • enableAppSecurity – Enables application security for the application. This action sets the mxe.useAppServerSecurity property to a value of 1, and updates the mxe.ldapUserManagement flag. This value is written to the database when the database is updated. • enableDB2TextSearch – Enables the full text search feature on a Db2 database. • reapplyAppServerTuning – Reapplies tuning configuration to an application server. • removeDatabaseConfiguration – Removes product configuration information from a previously configured database. • removeJ2EEConfiguration – Removes application server configuration that was added by the configuration tool. • updateApplication – Updates the Maximo Asset Management application by updating the database and redeploying application EAR files. This action should not be used in an upgrade scenario or when a new product is installed in an existing product.

Table 7. Maximo Asset Management command line configuration program parameters (continued)

Parameter name	Description
	• updateApplicationDBLite – Update the database using the DB Lite feature and then rebuild and redeploy the EARs. • updateDatabaseConfiguration – Updates existing database configuration values. • updateJ2eeConfiguration - Updates existing application server configuration values. • upgrade75Configuration - Performs database properties validation for your Maximo Asset Management 7.5 deployment to ensure a valid connection to the database, and also configures WebSphere Application Server for Maximo Asset Management 7.6. When you upgrade from Maximo Asset Management 7.5, you must configure a new instance of WebSphere Application Server. • validateAndUpdateDatabaseConfiguration – Validates reconfiguration command line interface tool input and then updates existing database configuration property values. • validateAndUpdateJ2eeConfiguration - Validates reconfiguration command line interface tool input and then updates existing database configuration property values. • validateDatabaseConfiguration - Validates database configuration values specified as input for the reconfiguration command line interface tool. • validateJ2eeConfiguration - Validates application server configuration values that are specified as input for the reconfiguration command line interface tool. • removeConfiguration - Removes database and application configuration performed by the configuration tool. The actions that modify the security setting for Maximo Asset Management also updates Maximo Asset Managementweb.xml files.
-additionalLangs	Adds one or more additional languages to the deployment. This parameter requires one or more locale abbreviations for input. For example, ES for Spanish.
-allowUpdateDB	The database update task is run to add the languages that are specified to the database.
-applicationServerName	Name of the application server.
-applicationServerNode	Name of the application server node.
-automatedbconfig	Automates the configuration of the database. Use this parameter to create the database instance, database users, the database, table spaces, and creates database schema.
-automatej2eeconfig	Automates the configuration of WebSphere Application Server. Using this parameter creates, for example, JMS queues and profiles.
-buildAndDeployEAR	Rebuilds and deploys application EAR files. Application EAR files must be rebuilt and redeployed for configuration changes to take effect in the application.
-buildears	Rebuilds application EAR files.

Table 7. Maximo Asset Management command line configuration program parameters (continued)

Parameter name	Description
-bypassJ2eeValidation	Skips the validation and configuration of the application server. If you use this parameter, then you must manually configure the application server before you can deploy Maximo Asset Management. Validation of a manually configured application server requires logging in to the application server with application server administrative credentials. If you do not want to provide those credentials to the configuration program, you can skip the validation task. If you use the bypassJ2eeValidation parameter, you cannot also use the following parameters: • applicationServerName • applicationServerNode • automatej2eeconfig • buildAndDeployEAR • createResourcesIfMissing • deploymaximoear • enableappsecurity • enableEnhancedNavigation • enableSkin • inputfile • j2eeserverport • usermanagement • wasuser • waspwd
-bypassUpdateDB	Specifies that the database update task is not run and the installation program does not update the database. Languages files for the locales that are specified are built into the application EAR file. Use this parameter if you have run the database update task and included the language files in the database through another method.
-createResourcesIfMissing	Creates any resources that are not found during configuration.
-db2_english_only	Specifies that alphanumeric data is stored as a varchar data type. Using this parameter limits you to using English in the user interface. If you do not use this parameter, alphanumeric data is stored as a vargraphic data type.
-db2textsearchport	Port that is used by the Db2 server for full text search.
-dbname	Name of the database.
-dbpwd	Password for the user ID that accesses the database.
-dbrxapwd	Password for the user ID used to access a remote middleware server.
-dbrxuser	User ID used to access a remote middleware server.
-dbserverhost	Host name of the database server.

Table 7. Maximo Asset Management command line configuration program parameters (continued)

Parameter name	Description
-dbserverport	Port name of the database server.
-dbuser	User ID that accesses the database.
-dbvendor	Database software name. • DB2 • Oracle • SQLServer
-deleteInstanceUsersAndGroups	Removes the instance owner and database user IDs and associated groups from the Db2 server. This parameter cannot be used with Microsoft SQL Server. The deleteInstanceUsersAndGroups parameter requires the dbrxauser and dbrxapwd and the dbuser and dbpwd parameters.
-deleteWASprofiles	Deletes the WebSphere Application Server profiles that are created for the application.
-deployDemoData	Includes sample data.
-deploymaximoear	Deploys Maximo application EAR file.
-enableappsecurity	Enables application security for the application. This parameter works the same as the enableAppSecurity action. This action sets the mxe.useAppServerSecurity property to a value of 1, and updates the mxe.ldapUserManagement flag. This value is written to the database when updated.
-enableEnhancedNavigation	Enables enhanced navigational elements in the user interface, including enhancements for switching between applications and viewing record lists. The enableEnhancedNavigation parameter must be used with the enableSkin parameter. If you enable enhanced navigation, and then you enable a different user interface skin with the -enableSkin parameter, you must re-enable enhanced navigation.
-enableMultiTenancy	Enables the multitenancy feature. Multitenancy refers to software or services that can be configured to serve multiple groups of clients that are referred to as tenants. Each group of tenants is served by an instance of the software that uses data that only they can access.

Table 7. Maximo Asset Management command line configuration program parameters (continued)

Parameter name	Description
-enableRestrictivePasswordPolicy	Enables a more restrictive password policy for Maximo Asset Management users. • Login attempts Standard policy allows 10 login attempts before the account is locked. Restrictive policy allows 3 login attempts before the account is locked. • Number of times that the forgotten password link can be used. Standard policy allows 5 uses of the forgotten password link before locking the account. Restrictive policy allows three uses of the forgotten password link before locking the account. • Password duration (days) Standard policy passwords never expire. Restrictive policy passwords expire after 90 days. • Password expiration warning (days) Standard policy does not warn the user that the account password is about to expire. Restrictive policy warns the user that the account password is about to expire seven days before it expires. • Password threshold Standard policy does not enforce a password threshold. Restrictive policy enforces a password threshold of 270 characters.
	• Password minimum character length Standard policy passwords must be at least six characters. Restrictive policy passwords must be at least eight characters. • Limit of allowed consecutive characters Standard policy has no restrictions to the amount of times a character can be repeated consecutively in a password. Restrictive policy allows a character to be repeated two times consecutively in a password value. • Password can be same value as user name Standard policy allows you to use the same value for the user name and password. Restrictive policy does not allow you to use the same value for the user name and password. • Number of numeric characters required in the password Standard policy does not require numeric characters in a password value. Restrictive policy requires one or more numeric characters in a password value. • Number of alphabetic characters required in the password Standard policy does not require alphabetic characters in a password value. Restrictive policy requires one or more alphabetic characters in a password value.

Table 7. Maximo Asset Management command line configuration program parameters (continued)

Parameter name	Description
-enableSkin	Change the appearance of the user interface. • Classic - The following properties are set to 0: – mxe.webclient.homeButtonHeaders – mxe.webclient.systemNavBar – mxe.webclient.tabBreadCrumbs – mxe.webclient.verticalLabels - Sets the following property to null: – mxe.webclient.skin • iot18 - When enhanced navigation is enabled, the following properties are set to a value of 1: – mxe.webclient.homeButtonHeaders – mxe.webclient.systemNavBar – mxe.webclient.tabBreadCrumbs - The following property is set to a value of 2: – mxe.webclient.verticalLabels - When enhanced navigation is not chosen, the following properties are set to a value of 0: – mxe.webclient.homeButtonHeaders – mxe.webclient.systemNavBar – mxe.webclient.tabBreadCrumbs – mxe.webclient.verticalLabels - Sets the following property: – mxe.webclient.skin=iot18 • tivoli09 - When enhanced navigation is enabled, the following properties are set to a value of 1: – mxe.webclient.homeButtonHeaders – mxe.webclient.systemNavBar – mxe.webclient.tabBreadCrumbs – mxe.webclient.verticalLabels - When enhanced navigation is not enabled, the following properties are set to a value of 0: – mxe.webclient.homeButtonHeaders – mxe.webclient.systemNavBar – mxe.webclient.tabBreadCrumbs – mxe.webclient.verticalLabels - Sets the following property: – mxe.webclient.skin=tivoli09

Table 7. Maximo Asset Management command line configuration program parameters (continued)

Parameter name	Description
	• tivoli13 When enhanced navigation is enabled, the following properties are set to a value of 1: – mxe.webclient.homeButtonHeaders – mxe.webclient.systemNavBar – mxe.webclient.tabBreadCrumbs – mxe.webclient.verticalLabels When enhanced navigation is not enabled, the following properties are set to a value of 0: – mxe.webclient.homeButtonHeaders – mxe.webclient.systemNavBar – mxe.webclient.tabBreadCrumbs – mxe.webclient.verticalLabels Sets the following property: – mxe.webclient.skin=tivoli13
-force	Indicates that an input property file updates the properties file and skips the validation of parameters input to the command line tool through an input properties file. When you use this parameter, you are not prompted for confirmation of the property update task.
-inputfile	Fully qualified path to the properties file that is used to set properties in an environment. Values that are specified as command line parameters for the configuration command line interface tool supersede values from the input file.
-j2eeserverhost	Host name of the domain manager of the application server. If deployment manager host name or server port is specified the thinwsadmin scripts are updated accordingly.
-j2eeserverport	Port name of the application server domain manager server. If deployment manager host name or server port is specified the thinwsadmin scripts are updated accordingly.
-j2eevendor	Application server software. • WebSphere • WebLogic
-removeCreatedArtifacts	Removes any artifacts that are created by the configuration tool. Examples include directories that are created by the configuration program, JMS objects, and the application server.
-removeInstance	Removes the database instance for Db2 and Oracle. This parameter cannot be used with Microsoft SQL Server. The removeInstance parameter requires the dbxouser and dbxapwd, and the dbuser and dbpwd parameters.
-setjdbcurl	Sets the JDBC connection URL string.

Table 7. Maximo Asset Management command line configuration program parameters (continued)

Parameter name	Description
-stopApplications	The Maximo Asset Management application server must be stopped when you add languages. If you do not use the stopApplications parameter with the addLanguages action, you must stop the application server manually before you use the addLanguages action. This parameter is used for WebSphere Application Server only.
-unsetjdbcurl	Removes the currently used JDBC connection URL string.
-updatedb	Runs the updatedb configuration task.
-usermanagement	Changes the security configuration of the existing Maximo deployment. • j2ee Change the security setting in Maximo so that both Maximo users and Maximo groups are managed through application server security mechanisms. • mixed Manage users through application server security mechanisms, and manage groups using Maximo.
-validateForNewDeploy	Validate middleware configuration. When this parameter is specified, validation is performed as if the tool was configuring the middleware. Additional configuration details are checked, including disk space availability and remote access credentials. If this parameter is not specified, validation is performed in the context of a component that is already established in the environment.
-validateUsers	Used with the enableAppSecurity action to validate users exist in the LDAP repository. If the users do not exist, the existing security model is not modified.
-waspwd	WebSphere Application Server administrator user ID password.
-wasrxapwd	Password for user ID to access remote WebSphere Application Server server host.
-wasrxauser	Operating system user ID used to access remote WebSphere Application Server host. Typically this user ID is defined either as Administrator or root.
-wasuser	WebSphere Application Server administrator user ID. This is the user ID that is used to log in to the WebSphere Application Server administrative client application. Typically, this user ID is defined as wasadmin.

Command line configuration program actions

Use the command line configuration program to configure new or existing deployments of Maximo Asset Management.

action updateDatabaseConfiguration

The **updateDatabaseConfiguration** action is used to update existing database configuration values.

```
-action updateDatabaseConfiguration [-force] [-buildAndDeployEAR]
[-dbserverhost hostname] [-dbserverport port number]
[-dbname database name] [-dbuser userid]
[-dbpwd password] [-dbrxauser userid]
[-dbrxapwd password] [-setjdbcurl jdbcurl]
[-unsetjdbcurl] [-inputfile path to input properties file]
```

action validateDatabaseConfiguration

Use the **validateDatabaseConfiguration** action to validate current database configuration properties. This action can be used to verify database properties before they are updated, or following an update action.

```
-action validateDatabaseConfiguration [-validateForNewDeploy]
[-dbserverhost hostname]
[-dbserverport port number]
[-dbname database name]
[-dbuser userid] [-dbpwd password]
[-dbrxauser userid]
[-dbrxapwd password] [-setjdbcurl jdbcurl]
[-unsetjdbcurl] [-enableMultiTenancy]
[-inputfile path to input properties file]
```

The following properties are required if the **-validateForNewDeploy** parameter is used.

- **Database.DB2.InstanceAdminGroup**
- **Database.DB2.InstanceAdminUserName** (Windows only)
- **Database.DB2.InstanceAdminPassword** (Windows only)
- **Database.DB2.FencedUser**
- **Database.DB2.FencedUserPassword**
- **Database.DB2.FencedGroupName**
- **Database.DB2.InstanceUserPassword**

These properties must be added manually to the `install.properties` file.

action validateAndUpdateDatabaseConfiguration

The **validateAndUpdateDatabaseConfiguration** action is used to both validate reconfiguration command-line interface tool input and then update existing database configuration property values.

```
-action validateAndUpdateDatabaseConfiguration [-validateForNewDeploy] [-force]
[-buildAndDeployEAR] [-dbserverhost hostname]
[-dbserverport port number] [-dbname database name]
[-dbuser userid] [-dbpwd password]
[-dbrxauser userid] [-dbrxapwd password]
[-setjdbcurl jdbcurl] [-unsetjdbcurl] [-enableMultiTenancy]
[-inputfile path to input properties file]
```

The following properties are required if the **-validateForNewDeploy** parameter is used.

- **Database.DB2.InstanceAdminGroup**
- **Database.DB2.InstanceAdminUserName** (Windows only)
- **Database.DB2.InstanceAdminPassword** (Windows only)
- **Database.DB2.FencedUser**

- **Database.DB2.FencedUserPassword**
- **Database.DB2.FencedGroupName**
- **Database.DB2.InstanceUserPassword**

These properties that must be added manually to the `install.properties` file.

The **-enableMultiTenancy** parameter must be used with the **-validateForNewDeploy** parameter.

action deployDatabaseConfiguration

The **deployDatabaseConfiguration** action is used to validate command-line configuration program input and define configuration property values for a new database for the currently deployed product. This action can be run after a successful **deployConfiguration** action.

```
-action deployDatabaseConfiguration [-buildAndDeployEAR] [-createResourcesIfMissing]
[-dbserverhost hostname] [-dbserverport port number]
\[-dbname database name] [-dbuser userid]
[-dbpwd password] [-dbrxauser userid] [-dbrxapwd password]
[-setjdbcurl jdbcurl] [-unsetjdbcurl] [-enableMultiTenancy]
[-deployDemoData]
[-inputfile path to input properties file] [-enableRestrictivePasswordPolicy]
```

The following properties are required if the **-createResourcesIfMissing** parameter is used.

- **Database.DB2.InstanceAdminGroup**
- **Database.DB2.InstanceAdminUserName** (Windows only)
- **Database.DB2.InstanceAdminPassword** (Windows only)
- **Database.DB2.FencedUser**
- **Database.DB2.FencedUserPassword**
- **Database.DB2.FencedGroupName**
- **Database.DB2.InstanceUserPassword**

These properties that must be added manually to the `install.properties` file.

action removeDatabaseConfiguration

The **removeDatabaseConfiguration** action is used to remove configuration settings from a previously configured database.

```
-action removeDatabaseConfiguration [-removeInstance] [-dbrxauser userid]
[-dbrxapwd password] [-dbuser userid]
[-dbpwd password] [-deleteInstanceUsersAndGroups]
```

action enableDB2TextSearch

The **enableDB2TextSearch** action is used to enable the full text search feature for a Db2 database.

```
-action enableDB2TextSearch [-db2textsearchport port number]
```

action updateJ2eeConfiguration

The **updateJ2eeConfiguration** action is used to update existing application server configuration values.

```
-action updateJ2eeConfiguration [-force] [-buildAndDeployEAR]
[-j2eeserverhost hostname] [-j2eeserverport port number]
[-wasuser userid] [-waspwd password]
[-applicationServerNode nodeName] [-applicationServerName appServerName]
[-inputfile path to input properties file]
```

action validateJ2eeConfiguration

The **validateJ2eeConfiguration** action is used to validate application server configuration values specified as input for the reconfiguration command-line interface tool.

```
-action validateJ2eeConfiguration [-validateForNewDeploy] [-j2eeserverhost hostname]
[-j2eeserverport port number] [-wasuser userid]
[-waspwd password] [-applicationServerNode nodeName]
[-applicationServerName appServerName] [-inputfile path to input properties file]
```

The following properties are required if the **-validateForNewDeploy** parameter is used and the **WAS.SibPersistMessages** property is set to true.

- **Database.DB2.FencedUser**
- **Database.DB2.FencedUserPassword**
- **Database.DB2.InstanceUserPassword**

These properties that must be added manually to the `install.properties` file.

action validateAndUpdateJ2eeConfiguration

The **validateAndUpdateJ2eeConfiguration** action is used to both validate reconfiguration command-line interface tool input and then update existing application server configuration property values.

```
-action validateAndUpdateJ2eeConfiguration [-force] [-validateForNewDeploy]
[-buildAndDeployEAR] [-j2eeserverhost hostname]
[-j2eeserverport port number] [-wasuser userid]
[-waspwd password] [-applicationServerNode nodeName]
[-applicationServerName appServerName]
[-inputfile path to input properties file]
```

The following properties are required if the **-validateForNewDeploy** parameter is used and the **WAS.SibPersistMessages** property is set to true.

- **Database.DB2.FencedUser**
- **Database.DB2.FencedUserPassword**
- **Database.DB2.InstanceUserPassword**

These properties must be added manually to the `install.properties` file.

action deployJ2eeConfiguration

The **deployJ2eeConfiguration** action is used to validate command line configuration program input and define configuration property values for a new application server for the currently deployed product. This action can be run after a successful **deployConfiguration** action.

```
-action deployJ2eeConfiguration [-bypassJ2eeValidation] [-buildAndDeployEAR]
[-createResourcesIfMissing] [-j2eeserverhost hostname]
[-j2eeserverport port number] [-wasuser userid]
[-waspwd password] [-applicationServerNode nodeName]
[-applicationServerName appServerName]
[-inputfile path to input properties file]
[-enableSkin Classic|tivolio9|tivolii3] [-enableEnhancedNavigation]
```

The following properties are required if the **-validateForNewDeploy** parameter is used and the **WAS.SibPersistMessages** property is set to true.

- **Database.DB2.FencedUser**
- **Database.DB2.FencedUserPassword**
- **Database.DB2.InstanceUserPassword**

These properties that must be added manually to the `install.properties` file.

action removeJ2EEConfiguration

The **removeJ2EEConfiguration** action is used to remove configuration settings from a previously configured application server. Items removed include domain manager and application server profiles, and JMS objects.

```
-action removeJ2EEConfiguration [-wasuser userid] [-waspwd password]  
[-wasrxuser userid] [-wasrxpwd password]  
[-removeCreatedArtifacts] [-deleteWasProfiles]
```

action deployConfiguration

Use the **deployConfiguration** action to configure the initial installation. This action is used for new Maximo Asset Management installation scenarios only. This action can configure multiple middleware products after they are installed. The **deployConfiguration** action requires the **inputfile** parameter and an input properties file populated with the configuration values you want to use.

```
-action deployConfiguration [-inputfile path to input properties file]  
[-dbvendor Oracle|DB2|SQLServer] [-j2eevendor WebSphere|WebLogic]  
[-bypassJ2eeValidation] [-automatedbconfig] [-automatej2eeconfig]  
[-usermanagement j2ee|mixed] [-buildears] [-deploymaximoeear]  
[-enableappsecurity] [-deployDemoData] [-enableMultiTenancy] [-db2_english_only]  
[-enableSkin Classic|tivoli09|tivoli13] [-enableEnhancedNavigation]  
[-enableRestrictivePasswordPolicy]
```

action removeConfiguration

The **removeConfiguration** action is used to removes database and application configuration that is performed by the configuration tool. This action is equivalent to running the **removeJ2EEConfiguration** and **removeDatabaseConfiguration** actions together

```
-action removeConfiguration -dbuser userid  
-dbpwd password -wasuser userid  
-waspwd password [-wasrxuser userid]  
[-wasrxpwd password] [-dbrxuser userid]  
[-dbrxpwd password] [-removeInstance] [-deleteInstanceUsersAndGroups]  
[-removeCreatedArtifacts] [-deleteWasProfiles]  
[-inputfile path to input properties file]
```

action reapplyAppServerTuning

The **reapplyAppServerTuning** action is used to reapply best practices application server tuning settings.

```
-action reapplyAppServerTuning [-wasuser userid]  
[-waspwd password] [-applicationServerNode nodeName]  
[-applicationServerName appServerName]
```

You must restart the application server after the settings are applied.

action enableAppSecurity

The **enableAppSecurity** action is used to enable application security for the application. This action sets the **mxe.useAppServerSecurity** property to a value of

1, and updates the **mx.e.ldapUserManagement** property according to the setting of the **-usermanagement** parameter. This value is written to the database when updated. The maximouiweb, maxrestweb, meaweb, and mboweb web.xml files are updated during this action.

```
-action enableAppSecurity -usermanagement {j2ee,mixed}
[-buildAndDeployEAR] [-validateUsers] [-force]
```

action disableAppSecurity

The **disableAppSecurity** action is used to disable application security for the application. This action sets the **mx.e.useAppServerSecurity** property to a value of 0. This value is written to the database when updated. Using this action reverts the security implementation to Maximo security for users and groups. The maximouiweb, maxrestweb, meaweb, and mboweb web.xml files are updated during this action.

```
-action disableAppSecurity [-buildAndDeployEar] [-force]
```

action updateApplication

The **updateApplication** action is used to update the application by updating the database and redeploying application EAR files. This action should not be used in an upgrade scenario or when a new product is installed in an existing product.

```
-action updateApplication [-updatedb] [-deploymaximoear]
[-enableSkin Classic|tivoli09|tivoli13] [-enableEnhancedNavigation]
[-enableRestrictivePasswordPolicy]
```

action addLanguages

Use the **addLanguages** action to configure additional languages for a deployment.

```
-action addLanguages [-additionalLangs locale1,locale2,locale3]
[-buildAndDeployEAR] [-allowUpdateDB | -bypassUpdateDB] [-stopApplications]
[-inputfile path to input properties file]
```

The application server must be stopped when you add languages. If you do not use the **stopApplications** parameter with the **addLanguages** action, you must stop the application server manually before you use the **addLanguages** action.

The following locale values are supported.

Table 8. Locales supported by the configuration program

Language	Locale
Arabic	ar
Brazilian Portuguese	pt_BR
Croatian	hr
Czech	cs
Danish	da
Dutch	nl
Finnish	fi
French	fr
German	de
Hebrew	he
Hungarian	hu
Italian	it

Table 8. Locales supported by the configuration program (continued)

Language	Locale
Japanese	ja
Korean	ko
Norwegian	no
Polish	pl
Russian	ru
Simplified Chinese	zh_CN
Slovak	sk
Slovenian	sl
Spanish	es
Swedish	sv
Traditional Chinese	zh_TW
Turkish	tr

action configureProducts

The **configureProducts** action should be used to configure more products that are installed after an initial installation and configuration. This action verifies a full installation and configuration of an existing product was completed successfully before it continues. This action can configure multiple products after they are installed. This action should be used in an upgrade scenario.

```
-action configureProducts [-updatedb] [-buildears] [-deploymaximoear]
```

action deployMiddlewareConfiguration

The **deployMiddlewareConfiguration** action is used to configures middleware after it is installed.

```
-action deployMiddlewareConfiguration [-inputfile path to input properties file]
```

The following properties can be included in the input properties file used with the **deployMiddlewareConfiguration** action.

Table 9. Properties that can be used in the deployMiddlewareConfiguration action input file

Category	Property
HTTP Server properties	IHS.HTTPPort
	IHS.InstallLocation
	IHS.WebserverName
LDAP server properties	LDAP.AdminDN
	LDAP.AdminPassword
	LDAP.BaseEntry
	LDAP.GroupSuffix
	LDAP.OrgContainerSuffix
	LDAP.ServerHostName
	LDAP.ServerPort
	LDAP.UserSuffix
	LDAP.Vendor

Table 9. Properties that can be used in the `deployMiddlewareConfiguration` action input file (continued)

Category	Property
General middleware configuration properties	MW.Operation
WebSphere properties	PLG.InstallLocation
	WAS.AdminPassword
	WAS.AdminUserName
	WAS.ApplicationServerName
	WAS.CellName
	WAS.DeploymentManagerNodeName
\	WAS.DeploymentManagerProfileName
	WAS.InstallLocation
	WAS.LDAPAutomatedConfig
	WAS.ND.AutomateConfig
	WAS.NodeName
	WAS.ServerProfileName
	WAS.SOAPConnectorPort
	WCT.InstallLocation

action upgrade75Configuration

The **upgrade75Configuration** action performs database properties validation for your Maximo Asset Management 7.5 deployment to ensure a valid connection to the database, and also configures WebSphere Application Server for Maximo Asset Management 7.6. When you upgrade from Maximo Asset Management 7.5, you must configure a new instance of WebSphere Application Server.

```
-action upgrade75Configuration [-inputfile path to input properties file]
[-dbvendor <Oracle|DB2|SQLServer>] [-j2eevendor <WebSphere|WebLogic>]
[-automatej2eeconfig] [-usermanagement <j2ee|mixed>]
[-enableappsecurity] [-bypassJ2eeValidation]
```

action updateApplicationDBLite

The **updateApplicationDBLite** action is used to update the database using the DB Lite feature and then rebuild and redeploy the EARs. This action should not be used in an upgrade scenario or when a new product is installed in an existing product.

```
-action updateApplicationDBLite [-preprocessor] [-updatedb]
[-buildears] [-deploymaximoeear] [-enableSkin tivoli09|tivoli13|classic]
[-enableEnhancedNavigation] [-disableEnhancedNavigation]
[-enableRestrictivePasswordPolicy]
```

The `-preprocessor` attribute can be used to prepare class files before they are built into the application EAR files. The non-lite version of the `updatedb` command can also perform this work, however, it requires that you stop the application server. If you use the `-preprocessor` attribute, you are not required to stop the application server while class files are prepared, decreasing the amount of downtime for your environment.

The `-updatedb` attribute can be used to update the database independently. When you use this attribute, the application server must be stopped. The `updatedb` process does not include preparing class files, which shortens the amount of time that your application server is down.

The `-preprocessor` and `-updatedb` attributes are mutually exclusive. You cannot use them together. The `-buildears` attribute can only be used with the `-preprocessor` attribute. The `-deploymaximoeear` attribute can only be used in conjunction with the `-updatedb` attribute.

action configureProductsDBLite

The **configureProductsDBLite** action should be used to configure products after an initial installation and configuration using the DB Lite feature. This action can configure multiple products after they are installed and should be used in an upgrade scenario.

```
-action configureProductsDBLite [-preprocessor] [-updatedb]
[-buildears] [-deploymaximoeear]
```

The `-preprocessor` attribute can be used to prepare class files before they are built into the application EAR files. The non-lite version of the `updatedb` command can also perform this work, however, it requires that you stop the application server. If you use the `-preprocessor` attribute, you are not required to stop the application server while class files are prepared, decreasing the amount of downtime for your environment.

The `-updatedb` attribute can be used to update the database independently. When you use this attribute, the application server must be stopped. The `updatedb` process does not include preparing class files, which shortens the amount of time that your application server is down.

The `-preprocessor` and `-updatedb` attributes are mutually exclusive. You cannot use them together. The `-buildears` attribute can only be used with the `-preprocessor` attribute. The `-deploymaximoeear` attribute can only be used in conjunction with the `-updatedb` attribute.

Configuration program properties

Maximo Asset Management properties can be modified with the command line configuration program by using an `input.properties` file. When you set a property value to a Windows path, you must use two consecutive backslashes, for example, `C:\\IBM\\WebSphere\\AppServer`. When you set property values to a Linux or UNIX path, use single forward slashes. For example, `/opt/IBM/db2/V10.5`.

Table 10. Maximo Asset Management properties

Category	Property	Definition
Shared database properties	<code>mxe.db.schemaowner</code>	Owner of the database schema. For example, <code>maximo</code> . This value is written to the database when updated.
	<code>mxe.db.user</code>	User ID that accesses the database.
	<code>mxe.db.password</code>	Password for the user ID that accesses the database.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.RemoteAccessUserName	Database server system user ID that is used for configure the database remotely. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.RemoteAccessPassword	Password for user ID named in Database.RemoteAccessUserName. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
Db2 Properties	Database.DB2.ServerHostName	Fully qualified host name of the Db2 server. For example, mymachine.mydomain.com. This value is written to the database when updated.
	Database.DB2.ServerPort	Database server port. For example, 50005. This value is written to the database when updated.
	Database.DB2.InstanceName	Name of the database instance. For example, ctginst1. This value is written to the database when updated. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.InstanceUserPassword	Password for the database instance owner This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.DB2.InstanceAdminGroup	Group for the instance administrator. For example, ctgiadm1. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.DatabaseName	Name of the database. For example, maxdb76. This value is written to the database when updated.
	Database.DB2.InstallLocation	Install location of the database. For example, /opt/IBM/db2/V10.5. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.LogFileSize	Set the size for transaction logs. For example, 8192. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.AppCtlHeapSize	Application control heap size. For example, 1024. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.ApplHeapSize	Application heap size. For example, 1024. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.DB2.LockListSize	Size that is allocated to the lock list. For example, AUTOMATIC. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.LogSecond	Number of secondary log files allowed. For example, 100. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.ServiceUser	User ID used to autostart. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified. This property is only required if Db2 is installed on a Windows system.
	Database.DB2.ServicePassword	Password for Database.DB2.ServiceUser. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified. This property is only required if Db2 is installed on a Windows system.
	Database.DB2.ExtentSize	Number of pages per extent (group of pages). For example, 32. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.DB2.FencedUser	Fenced user ID for Db2 on Linux or UNIX systems. For example, db2fenc1. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.FencedUserPassword	Password for the fenced user ID for Db2 on Linux or UNIX systems. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.FencedGroupName	Default group for database fenced user. For example, ctgfgrp1. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified. This property is only required if Db2 is installed on a Linux or UNIX system.
	Database.DB2.AuthType	Method Db2 uses to authenticate users. For example, server. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.DataTablespaceName	Db2 table space name for the product database. For example, maxdata.
	Database.DB2.BufferPoolName	Db2 buffer pool name. For example, MAXBUFPOOL. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.DB2.BufferPoolSize	Size of the buffer pool. For example, 4096. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.DataTablespaceLocation	Location of Db2 database table space data files. For example, CTGDAT. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.DataTablespaceSize	Table space size, which is measured in Mb. For example, 5000. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.TempTablespaceName	Temporary table space name. For example, maxtemp. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.TempTablespaceLocation	Location of temporary table space. For example, CTGTMP. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DB2.TempTablespaceSize	Temporary table space size, which is measured in Mb. For example, 1000. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.DB2.IndexTablespaceName	Index table space name. For example, maxdata.
	Database.DB2.IndexTablespaceLocation	Location of index table space. For example, CTGDAT. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
	Database.DB2.IndexTablespaceSize	Index table space size, which is measured in Mb. For example, 5000. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
	Database.DB2.InstanceAdminUserName	Administrative user or the database instance. For example, db2admin. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified. For Unix and Linux platforms, this value must be the same as the instance owner.
	Database.DB2.InstanceAdminPassword	Password for the user ID specified for Database.DB2.InstanceAdminUserName . This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified. createResourcesIfMissing
Oracle	Database.Oracle.SchemaPassword	Password for the schema owner.
	Database.Oracle.InstanceName	Oracle instance name. This value is written to the database when updated.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.Oracle.SoftwareOwner	Owner of the software installation. For example, oracle. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.Oracle.SoftwareOwnerPassword	Password for the user ID listed in Database.Oracle.SoftwareOwner. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.Oracle.InstallLocation	Oracle installation location. For example, /opt/app/oracle/product/10.2.0/db_1. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.Oracle.DataTablespaceName	Oracle table space name for the product database. For example, maxdata.
	Database.Oracle.InstanceLocation	Oracle instance location. For example, /opt/app/oracle/product/10.2.0/db_1. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.Oracle.DataTablespaceSize	Table space size, which is measured in Mb. For example, 5000. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.Oracle.TempTablespaceName	Temporary table space name. For example, maxtemp. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.Oracle.TempTablespaceSize	Temporary table space size, which is measured in Mb. For example, 1000. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.Oracle.IndexTablespaceName	Index table space name. For example, maxdata.
	Database.Oracle.IndexTablespaceSize	Index table space size, which is measured in Mb. For example, 1000. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.Oracle.ServerHostName	Fully qualified host name of the Oracle server.
	Database.Oracle.ServerPort	Port number that is used by Oracle. For example, 1521. This value is written to the database when updated.
	Database.DBUserName	Oracle DBA user name. For example, sys. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.
	Database.DBAPassword	Password for user ID listed for Database.DBUserName. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
Microsoft SQL Server	Database.SQL.DatabaseName	Name of the database. For example, maxdb76. This value is written to the database when updated.
	Database.SQL.DataFileName	A way to specify the name of the data file used for the database. For example, maxdb76_dat. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
	Database.SQL.DataFileMaxSize	Maximum size for data file for the database.
	Database.SQL.DataFileSize	Initial size for data file for the database in kb. For example, 5000. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
	Database.SQL.LogFileName	A way to specify the name for the database transaction log file. For example, maxdb76_log. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
	Database.SQL.LogFileSize	Microsoft SQL Server transaction log file size. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
	Database.SQL.DataFilegroupName	Database logical name file group. For example, PRIMARY. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	Database.SQL.ServerHostName	Host name of the database server. For example, myhost.mydomain.com.
	Database.SQL.ServerPort	Database server port. For example, 1433. This value is written to the database when updated.
	Database.SQL.InstanceAdminUserName	Administrative user for the Microsoft SQL Server instance. Used during installation for creating and modifying the database and database user. For example, sa. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
	Database.SQL.InstanceAdminPassword	Administrative user password. This property is only required if the createResourcesIfMissing , validatefornewdeploy , or automatedbconfig parameters are specified.
WebSphere Application Server Network Deployment	WAS.InstallLocation	Installation location for WebSphere Application Server Network Deployment. For example, C:\IBM\WebSphere\AppServer. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.DeploymentManagerHostName	Host name of the WebSphere Application Server Network Deployment deployment manager. This value is written to the database when updated.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.DeploymentManagerProfileName	WebSphere Application Server Network Deployment profile name. For example, ctgDmgr01. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.DeploymentManagerProfileRoot	Location of the WebSphere Application Server Network Deployment profile. For example, C:\IBM\WebSphere\AppServer\profiles\ctgDmgr01 This property is only required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.NodeName	WebSphere Application Server Network Deployment node name. For example, ctgNode01
	WAS.ApplicationServerName	WebSphere Application Server Network Deployment application server name. For example, MXServer. This value is written to the database when updated.
	WAS.CellName	WebSphere Application Server Network Deployment cell name. For example, ctgCell01.
	WAS.AdminUserName	WebSphere Application Server Network Deployment administrator name. For example, wasadmin.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.AdminPassword	WebSphere Application Server Network Deployment administrator password.
	WAS.RemoteAccessUserName	WebSphere Application Server Network Deployment deployment manager system user ID used for tasks such as copying Integrated Solutions Console web archive files and fetching the keystore. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.RemoteAccessPassword	WebSphere Application Server Network Deployment deployment manager system user password. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SOAPConnectorPort	SOAP port for WebSphere Application Server Network Deployment deployment manager. For example, 8879.
	WAS.VirtualHost	Name of the WebSphere Application Server Network Deployment virtual host. For example, maximo_host.
	WAS.WebServerHostName	Host name where the HTTP server is located.
	WAS.SibName	Name of the service integration bus. For example, intjmsbus.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.SibHiMsg	Service integration bus high message count. For example, 500000. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatej2eeconfig parameters are specified. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.WebServerName	Name of the WebSphere Application Server Network Deployment web server. Used to manage HTTP server from within WebSphere Application Server Network Deployment. For example, webserver1.
	WAS.SibPersistMessages	Binary value that indicates if service integration bus messages are persisted in either the product database or a local derby database. A value of true indicates that the messages are persisted. This property is only required if the createResourcesIfMissing, validatefornewdeploy, or automatej2eeconfig parameters are specified. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.SibDSName	Service integration bus data source name that is created to access the service integration bus persistence store. For example, intjmsds. This property is only required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDBName	Name of the service integration bus messages database. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDBInstance	Instance name of the service integration bus database. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDBInstancePassword	IBM Db2 instance users password for the SIB IBM Db2 data store. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.SibDBServerName	Server name of the system that is hosting the service integration bus message database. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDBServerPort	Database server port for the database that contains the service integration bus messages. For example, 50005. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDBUserName	User ID used to access the persistence data store database for service integration bus messages. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.SibDBUserPass	Password for user ID named in WAS.SibDBUserName. This property is only required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDBInstallDir	Where the service integration bus database is installed. For example, c:\program files\ibm\sqllib. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDbFencedUser	Fenced user ID for the service integration bus database. This property is only used for databases that are hosted on Linux and UNIX systems. For example, db2fenc1. This property is required if the WAS.SibPersistMessages property is set to true. This property is required if the database is hosted on a Linux or UNIX system. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.SibDbFencedPassword	Password for the fenced user ID for the service integration bus database. This property is required if the WAS.SibPersistMessages property is set to true. This property is required if the database is hosted on a Linux or UNIX system. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDbInstanceAdminUser	Instance owner for the service integration bus database. This property is required if the WAS.SibPersistMessages property is set to true. This property is required if the database is hosted on a Windows system. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDbInstanceAdminPassword	Password for the instance owner of the service integration bus database. This property is required if the WAS.SibPersistMessages property is set to true. This property is required if the database is hosted on a Windows system. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.SibDbRemoteAccessUser	Database server system user that is used to configure the service integration bus remotely. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.SibDbRemoteAccessPassword	Password for user ID named in WAS.SibDbRemoteAccessUser. This property is required if the WAS.SibPersistMessages property is set to true. This property is required in the properties file that is specified in one of the following properties. • WAS.MIFSIBPropertiesFile • WAS.CronSIBPropertiesFile • WAS.UISIBPropertiesFile
	WAS.VmmGroupRDN	Relative Distinguished Name of the location of virtual member manager groups. For example, ou=groups,ou=SWG,o=IBM,c=US.
	WAS.VmmUserRDN	Relative Distinguished Name of the location of virtual member manager users. For example, ou=users,ou=SWG,o=IBM,c=US.
	WAS.UseClustersForDeploy	Deploy the application EAR to a cluster. For example, true.
	WAS.UIClusterName	Name of the cluster that manages UI tasks. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.WAS.UIEnableJMS	Enable or disable JMS for Maximo Enterprise Adapter for the UI cluster. For example, true. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
	WAS.UISIBPropertiesFile	File that contains SIB persistence properties if you are persisting messages in the UI clusters bus. For example, c:\sibdb_ui.properties. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
	WAS.CronClusterName	Name of the cluster that manages cron tasks. For example, maximocron. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
	WAS.CronEnableJMS	Enable JMS for Maximo Enterprise Adapter for the cron task cluster. For example, true. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
	WAS.CronSIBPropertiesFile	File that contains SIB persistence properties if you are persisting messages in the cron clusters bus. For example, c:\sibdb_cr.properties. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
	WAS.ReportingClusterName	Name of the cluster that manages reporting tasks. For example, maximorpt. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	WAS.MIFClusterName	Name of the cluster that manages Maximo Integration Framework tasks. For example, maximomea. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
	WAS.MIFEnableJMS	Enable JMS for Maximo Enterprise Adapter for the Maximo Integration Framework task cluster. For example, true. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
	WAS.MIFSIBPropertiesFile	File that contains SIB persistence properties if you are persisting messages in the Maximo Integration Framework clusters bus. For example, c:\sibdb_mif.properties. Set a value for this parameter if WAS.UseClustersForDeploy is set to true.
Multi-tenancy	mt.sysprovider.tenantcode	Tenant code identifier for the multi-tenancy system provider. For example, MTM. This property is required to enable multi-tenancy.
	mt.sysprovider.desc	Description of the multi-tenancy manager.
	mt.configmanager.adminuserid	User ID of the multi-tenancy configuration manager. For example, maxadmin. This property is required to enable multi-tenancy. This value can be the same value used for the mtadminuser user.
	mt.configmanager.adminpassword	Password for the User ID of the multi-tenancy configuration manager. This property is required to enable multi-tenancy. This value can be the same value used for the mtadminpwd value.

Table 10. Maximo Asset Management properties (continued)

Category	Property	Definition
	mt.configmanager.tenantcode	Tenant code identifier for the multi-tenancy configuration manager. For example, GA. This property is required to enable multi-tenancy.
	mt.configmanager.desc	Description of the multi-tenancy global administrator.
	mt.configmanager.dbuser	User ID of the multi-tenancy configuration manager used to connect to the database. For example, ADMIN. This property is required to enable multi-tenancy. This value can be the same value used for the mtdbuser user.
	mt.configmanager.dbpassword	Password for the user ID of the multi-tenancy configuration manager that is used to connect to the database. This property is required to enable multi-tenancy. This value can be the same value used for the mtdbpwd value.
	mxe.mt.enabled	Value that indicates whether multi-tenancy is enabled. For example, a value of 1 indicates that multi-tenancy is enabled. A value of 0 indicates that multi-tenancy is not enabled for the product.
	mxe.mt.db.adminuser	THIS PROPERTY IS NO LONGER USED.
	mxe.mt.db.adminrole	Admin role that has permission to access template data when tenants are initially provisioned. The default value is MXTMPLT. However, users can create a different role and specify that value for the property.
	mxe.mt.demo.extratenants	Number of sample tenants to create when you enable multi-tenancy. For example, 10. This property is set in the <code>maximo.properties</code> file during the maxinst operation.

Chapter 14. Backup and restoration

Like all important business data, it is a good idea to establish a process and schedule for backing up Maximo Asset Management data.

Back up and restore middleware application data using the methods described in the documentation for that product is important. Also, establish a process for backing up data contained on the Maximo Asset Management administrative workstation.

The default installation directory on the Maximo Asset Management administrative workstation is C:\ibm. This directory contains the critical files for your Maximo Asset Management deployment, which includes all class files and customizations that have been performed in your environment, the current Enterprise Archive (EAR) file, and the properties files and installation tools used for your environment. Plan to back up Maximo Asset Management administrative workstation data just after initial deployment and schedule periodic backups on an ongoing basis.

Backing up the administrative workstation

It is recommended that you back up all Maximo Asset Management middleware applications and Maximo Asset Management administrative workstation on a regular basis.

About this task

The default installation directory on the administrative workstation is \ibm. This directory contains the critical files for your Maximo Asset Management deployment.

Specifically, the administrative workstation contains the following items:

- Class files and customizations performed in your environment.
- The current Enterprise Archive (EAR) file that was deployed to the application server.
- The properties files and installation tools used for your environment.

It is important to make a back up of the database at the same time that you back up the administrative workstation. During restoration, you restore the database back up at the same time you restore the administrative workstation back up it was paired with.

To back up critical Maximo Asset Management information, complete the following steps:

Procedure

1. Back up the Maximo Asset Management database, J2EE server, and authentication server information using the instructions provided by your middleware vendors.
2. Create a backup of the installation directory. By default, this directory is \IBM\SMP. Ensure that all file permissions are preserved.

3. Back up IBM Installation Manager agent data and shared files for recovery with IBM Business Process Manager (BPM). Refer to the IBM Support site for more information (<http://www-01.ibm.com/support/docview.wss?uid=swg21665878>).

Restoring the administrative workstation

This section details how to restore previously backed up Maximo Asset Management administrative workstation information. This information can be used to return an existing Maximo Asset Management administrative workstation to a previous state.

Before you begin

It is important to restore the back up of the database that was made when you backed up the administrative workstation. A database back up should be restored with the administrative workstation back up it was paired with.

About this task

To restore Maximo Asset Management information to an administrative workstation, complete the following steps:

Procedure

1. Restore the database back up that was paired with the administrative workstation back up you are restoring.
2. Log on to the target administrative system with the same user ID that was used to install the product on the existing administrative workstation.
3. Copy the Maximo Asset Management installation files and directories to the file system of the target administrative system. You must maintain the directory structure of the original installation. For example, if the Maximo Asset Management installation directory on the existing administrative system is \IBM\SMP, you cannot copy those files to a \NewAdminWS\IBM\SMP directory on the target administrative workstation.

Chapter 15. Uninstalling the product

Uninstalling Maximo Asset Management version 7.6.1 includes removing configuration values from Maximo Asset Management and associated middleware, and then uninstalling Maximo Asset Management.

Maximo Asset Management uninstallation is a comprehensive procedure and does not support partial removal of individual components or process managers, including process managers that are deployed by other products. Process managers of previously deployed products are also removed when you uninstall Maximo Asset Management.

Maximo Asset Management can only be uninstalled using the Maximo Asset Management installation and configuration programs as directed. Do not use other methods to attempt to uninstall Maximo Asset Management, such as using the Add/Remove Programs panel.

After the Maximo Asset Management uninstallation process is complete, you can reinstall Maximo Asset Management by using the Maximo Asset Management installation and configuration programs.

Remove Maximo Asset Management configuration

The first step to uninstall Maximo Asset Management is to remove configuration values using the Maximo Asset Management configuration program.

About this task

If you choose the option to delete the database instance, table spaces, the database, and the database instance are removed. The instance user, database users, and system users that were created with the configuration program can also be removed. For WebSphere Application Server Network Deployment, specify credentials for the WebSphere administrative user to uninstall the Maximo Asset Management application. If you choose the option to delete WebSphere artifacts, the application server and JMS queue information are removed.

Procedure

1. Log on to the WebSphere Application Server Network Deployment server with the WebSphere Application Server admin console and stop all of the Maximo Asset Management applications.
2. If the Maximo Asset Management configuration program is not open, start it from the Maximo Asset Management launchpad. In the launchpad navigation pane, click **Configure Product**, specify Maximo Asset Management installation location, and then click **Launch the Tivoli's Process Automation Suite configuration program**.
3. In the IBM Maximo Asset Management configuration operations page, click **Remove Product Configuration Information**.
4. In the Remove Product Configuration Information panel, specify credentials to access the database and WebSphere Application Server Network Deployment servers you previously configured for Maximo Asset Management.
5. Click **Finish**, and then **OK** to confirm.

Removing WebSphere Application Server Network Deployment configuration

Removing WebSphere Application Server Network Deployment configuration with the Maximo Asset Management configuration program deletes all configuration data.

Procedure

1. If the Maximo Asset Management configuration program is not open, start it from the Maximo Asset Management launchpad. In the launchpad navigation pane, click **Configure Product**, specify Maximo Asset Management installation location, and then click **Launch the Tivoli's Process Automation Suite configuration program**.
2. In the IBM Maximo Asset Management configuration operations page, click **Unconfigure WebSphere Application Server**.
3. In the Unconfigure WebSphere panel, specify credentials for the WebSphere administrative user to remove WebSphere Application Server Network Deployment profile information, and then click **Next**.
4. In the Unconfigure Middleware panel, select the **Unconfigure WebSphere Application Server Network Deployment** option, click **Finish**, and then **OK** to confirm.

Uninstalling Maximo Asset Management and middleware

Use the Installation Manager software to uninstall Maximo Asset Management and any middleware that was installed with the Maximo Asset Management installation program.

About this task

After you use the Maximo Asset Management configuration program to unconfigure Maximo Asset Management and associated middleware, use the Installation Manager software to uninstall previously installed components. You must run Installation Manager locally on the system that hosts the component you want to uninstall.

Procedure

1. Stop all Db2 and WebSphere Application Server Network Deployment processes on the system.
2. Open a command prompt and start Installation Manager.

Windows	UNIX
C:\Program Files\IBM\Installation Manager\eclipse\IBMIM.exe	IBMIM.sh

3. From the IBM Installation Manager interface, select **Uninstall**.
4. Select the packages that you want to remove and then click **Next**.
5. Review the package summary information and click **Uninstall** to remove the selected packages.

What to do next

Log files and other historical data is left behind for evaluation purposes. If you would like to reinstall the product in the same directory as before, you must first delete the directory completely before attempting the next installation.

Notices

This information was developed for products and services offered in the US. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those

websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample

programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

IBM Online Privacy Statement

IBM Software products, including software as service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session and persistent cookies that collect each user's name, user name, password, or other personally identifiable information for purposes of session management, authentication, single sign-on configuration or other usage tracking or functional purposes. These cookies can be disabled, but disabling them will also likely eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> in the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

Index

A

- action addLanguages 121
- action configureProducts 122
- action configureProductsDBLite 124
- action deployConfiguration 120
- action deployDatabaseConfiguration 118
- action deployJ2eeConfiguration 119
- action
 - deployMiddlewareConfiguration 122
- action disableAppSecurity 121
- action enableAppSecurity 121
- action enableDB2TextSearch 118
- action reapplyAppServerTuning 120
- action removeConfiguration 120
- action
 - removeDatabaseConfiguration 118
- action removeJ2EEConfiguration 120
- action updateApplication 121
- action updateApplicationDBLite 123
- action updateDatabaseConfiguration 117
- action updateJ2eeConfiguration 119
- action upgrade75Configuration 123
- action validate And Update Database Configuration 117
- action validate And Update J2ee Configuration 119
- action
 - validateDatabaseConfiguration 117
 - validateJ2eeConfiguration 119
- administrative workstation
 - backing up 147
 - restoring 148

B

- backup 147

C

- command line configuration program
 - input properties files 108
 - parameters 109
- Command line configuration program actions 117
- configuration 96
- configuration actions
 - addLanguages 121
 - configureProducts 122
 - configureProductsDBLite 124
 - deployConfiguration 120
 - deployDatabaseConfiguration 118
 - deployJ2eeConfiguration 119
 - deployMiddlewareConfiguration 122
 - disableAppSecurity 121
 - enableAppSecurity 121
 - enableDB2TextSearch 118
 - reapplyAppServerTuning 120
 - removeConfiguration 120
 - removeDatabaseConfiguration 118
 - removeJ2EEConfiguration 120

- configuration actions (*continued*)
 - updateApplication 121
 - updateApplicationDBLite 123
 - updateDatabaseConfiguration 117
 - updateJ2eeConfiguration 119
 - upgrade75Configuration 123
 - validate And Update Database Configuration 117
 - validate And Update J2ee Configuration 119
 - validateDatabaseConfiguration 117
 - validateJ2eeConfiguration 119
- configure Maximo Asset Management silently 83
- configure middleware silently 83
- configuring
 - database server 21
 - silent 81
- configuring Maximo Asset Management
 - command line configuration program 107
 - validate configuration parameters from the command line 108
- continuous inbound (CQIN) JMS queue creating 49
- CQINERR JMS queue creating 52

D

- data source
 - manually creating for the persistent store 35
- database server 21
- Db2
 - manual configuration, v11.1 21
- DB2 v11.1
 - installing 5, 67
- directory server
 - manually configuring 25

E

- EAR files
 - building manually 103
 - maintaining 103
- error queue 51

H

- HTTPOnly
 - configuring 87

I

- IBM Security Directory Server
 - manually configuring 26

- IBM WebSphere Application Server
 - Network Deployment HTTPOnly 87

- install
 - automatic middleware configuration 3
 - clustered environment 65
- install silently 78
- installation
 - automatically configuring existing middleware 13
 - deploying using manual middleware configuration 21
 - deploying with manually configured middleware 19
 - preparing 1
 - program logs 89
- Installation
 - post-installation tasks 96
- Installation Manager
 - installing silently 77
- installation program
 - logs 89
- installing
 - silent 75

J

- J2EE server
 - manually configuring 32
- JMS activation specification
 - creating for the continuous inbound queue (CQIN) 50
 - creating for the inbound error queue (CQINERR) 53
- JMS connection factory
 - creating 48
- JMS queues
 - manually configure 44

M

- Maximo Asset Management 63
 - configuring in a cluster environment 73
 - configuring with the Maximo Asset Management configuration program 9, 16, 59
 - installing version 7.6 8, 15, 58, 72
 - remove configuration 149
 - uninstalling 150
- Media
 - Installation 1
- Microsoft Active Directory
 - configuring 30
- Microsoft SQL Server
 - manual configuration 23
- middleware 75, 81
 - remove configuration silently 84

- middleware configuration
 - silent sample response files 82

N

- node agent
 - creating as a Windows service 44
- NOTF JMS queue
 - creating 9, 17, 60
- NOTFERR JMS queue
 - creating 10, 17, 61

P

- password
 - updating in response files 77
- post installation 91
- prerequisite 75, 81
- product
 - remove configuration silently 84
- product configuration program
 - overview 1
- product installation program
 - overview 1
- profiles
 - creating in WebSphere 32
- properties
 - Maximo Asset Management 124

R

- remove configuration
 - Maximo Asset Management 149
 - WebSphere Application Server Network Deployment 150
- restoration 147

S

- sequential inbound (SQIN) JMS queue
 - creating 49
- sequential outbound (SQOUT) JMS queue
 - creating 50
- service integration bus
 - adding a server 45
- service integration bus destination
 - creating for the continuous inbound (CQINBD) queue 46
 - creating for the inbound error queue (CQINERRBD) queue 51
 - creating for the sequential inbound (SQINBD) queue 47
 - creating for the sequential outbound (SQOUTBD) queue 47
- silent install 78, 83
 - sample response files 76
- silent installation
 - uninstallation 79
- silent response file
 - installation 75
 - Maximo Asset Management
 - configuration 82
 - middleware configuration 81
- SSL
 - configuring 4, 14, 67

U

- uninstall
 - Maximo Asset Management 150
 - middleware 150
 - product 149
- UpdateDB Lite
 - update database 63
- users
 - groups
 - synchronizing 99
 - synchronizing 99

V

- VMM
 - manual configuration 53

W

- WebSphere
 - manually creating profiles 32
- WebSphere Application Server Network Deployment
 - configuration tasks 37
 - install Maximo Asset Management applications 105
 - manually configuring 32
 - manually uninstalling 104
 - remove configuration 150
- WebSphere Application Server Network Deployment servers
 - configuring application server cluster profiles 69
 - configuring cluster members on additional WebSphere nodes 71
 - preparing for Maximo Asset Management configuration 7, 14, 69, 71
- WebSphere Application Server Network Deployment v9.0.0.7
 - installing 6, 68
- Work Center
 - manually building WAR file 104



Printed in USA