

Debug Tool for z/OS
Debug Tool Utilities and Advanced Functions for z/OS



User's Guide

Version 5 Release 1

Debug Tool for z/OS
Debug Tool Utilities and Advanced Functions for z/OS



User's Guide

Version 5 Release 1

Note!

Before using this information and the product it supports, be sure to read the general information under “Notices” on page 355.

Fourth Edition (July 2005)

| This edition applies to Debug Tool for z/OS, Version 5 Release 1 (Program Number 5655-M18), with the PTF for
| APAR PK07204 applied, which supports the following compilers:

- AD/Cycle C/370 Version 1 Release 2 (Program Number 5688-216)
- C/C++ for MVS/ESA Version 3 (Program Number 5655-121)
- C/C++ feature of OS/390 (Program Number 5647-A01)
- C/C++ feature of z/OS (Program Number 5694-A01)
- OS/VS COBOL, Version 1 Release 2.4 (5740-CB1) - with limitations
- VS COBOL II Version 1 Release 3 and Version 1 Release 4 (Program Numbers 5668-958, 5688-023) - with limitations
- COBOL/370 Version 1 Release 1 (Program Number 5688-197)
- COBOL for MVS & VM Version 1 Release 2 (Program Number 5688-197)
- COBOL for OS/390 & VM Version 2 (Program Number 5648-A25)
- Enterprise COBOL for z/OS and OS/390 Version 3 (Program Number 5655-G53)
- High Level Assembler for MVS & VM & VSE Version 1 Release 4 (Program Number 5696-234)
- | • OS PL/I Version 2 Release 1, Version 2 Release 2, Version 2 Release 3 (Program Numbers 5668-909, 5668-910) -
| with limitations
- PL/I for MVS & VM Version 1 Release 1 (Program Number 5688-235)
- VisualAge PL/I for OS/390 Version 2 Release 2 (Program Number 5655-B22)
- Enterprise PL/I for z/OS and OS/390 Version 3 (Program Number 5655-H31)

Parts of this edition apply to Debug Tool Utilities and Advanced Functions for z/OS, Version 5 Release 1 (Program Number 5655-M19).

This edition also applies to all subsequent releases and modifications until otherwise indicated in new editions or technical newsletters.

You can order publications online at www.ibm.com/shop/publications/order, or order by phone or fax. IBM Software Manufacturing Solutions takes publication orders between 8:30 a.m. and 7:00 p.m. Eastern Standard Time (EST). The phone number is (800)879-2755. The fax number is (800)445-9269.

You can find out more about Debug Tool by visiting the IBM Web site for Debug Tool at:
<http://www.ibm.com/software/awdtools/debugtool>

© Copyright International Business Machines Corporation 1992, 2004. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this document xi

Who might use this document	xi
Accessing z/OS licensed documents on the Internet	xi
Using LookAt to look up message explanations	xii
How this document is organized	xii
Terms used in this document	xv
How to read syntax diagrams	xvi
Symbols	xvi
Syntax items.	xvi
Syntax examples	xvii
How to send your comments.	xviii

Summary of changes xix

Debug Tool for z/OS Version 5.1 with PTF for	
APAR PK07204 applied	xix
Debug Tool for z/OS Version 5.1 with PTF for	
APAR PK00675 applied	xix
Debug Tool for z/OS Version 5.1 with PTF for	
APAR PQ94401 applied	xix
Debug Tool for z/OS Version 5.1	xx

Part 1. Getting started with Debug Tool 1

Chapter 1. Debug Tool: overview 3

Debug Tool interfaces	4
Full-screen mode	4
Batch mode.	5
Remote debug mode.	5

Chapter 2. Debug Tool Utilities and Advanced Functions: introduction 7

Debug Tool Utilities: creating and managing setup	
files	8
Debug Tool Utilities: converting, compiling, and	
linking	8
Debug Tool Utilities: preparing assembler programs	8
Debug Tool Utilities: conducting code coverage.	9
Debug Tool Utilities: preparing IMS run-time	
environment	9
Debug Tool Utilities: Load Module Analyzer.	9
Starting Debug Tool Utilities	9

Chapter 3. Debugging a program in full-screen mode: introduction 11

Compiling or assembling your program with the	
proper compiler options	11
Starting Debug Tool	12
Stepping through a program.	14
Running your program to a specific line.	14
Setting a breakpoint	14
Displaying the value of a variable.	15
Changing the value of a variable	16

Skipping a breakpoint	16
Clearing a breakpoint	16
Recording and replaying statements	17
Stopping Debug Tool	18

Part 2. Preparing your program for debugging 19

Chapter 4. Planning your debug session and collecting resources 21

Do you want your program to have hooks?	21
Do you want to reference variables during your	
debug session?	22
Do you want full debug capability or smaller	
application size and higher performance?	22
When do you want to start Debug Tool and when	
do you want it to gain control?.	23
Do you want to use Debug Tool in full-screen mode,	
in batch mode, or in remote debug mode?	24
Collecting your resources.	24

Chapter 5. Preparing a COBOL program 25

Compiling a COBOL program with the TEST	
compiler option	25
Converting an OS/VS COBOL program to 1985	
COBOL Standard	27

Chapter 6. Preparing an OS/VS COBOL program 29

Compiling your OS/VS COBOL program	29
Creating the EQALANGX file	29
Link-editing your program	31

Chapter 7. Preparing a PL/I program 33

Compiling a PL/I program with the TEST compiler	
option	33
Compiling a Enterprise PL/I program on an HFS	
file system.	34
Compiling a PL/I for MVS & VM or OS PL/I	
program	34

Chapter 8. Preparing a C program 37

Compiling a C program with the TEST compiler	
option	37
Compiling a C program on an HFS file system	39
Rules for the placement of hooks in functions and	
nested blocks.	39
Rules for placement of hooks in statements and	
path points	39
Compiling your C program with the #pragma	
statement	40

Chapter 9. Preparing a C++ program . . . 41

Compiling a C++ program with the TEST compiler option	41
Compiling a C++ program on an HFS file system	42
Rules for the placement of hooks in functions and nested blocks	42
Rules for the placement of hooks in statements and path points	42

Chapter 10. Preparing an assembler program 45

Before you begin	45
Assembling your program	46
Creating the EQALANGX file	46
Assembling your program and creating EQALANGX	47
Link-editing your program	48

Chapter 11. Preparing a DB2 program 49

Precompiling DB2 programs for debugging.	49
Compiling DB2 programs for debugging	50
Linking DB2 programs for debugging	50
Binding DB2 programs for debugging	51

Chapter 12. Preparing a DB2 stored procedures program 53

Chapter 13. Preparing a CICS program 55

Link-editing EQADCCXT into your program	55
Creating and storing a DTCN profile	56
Sharing DTCN repository profile items among CICS systems.	60
Using CADP to manage debugging profiles	61
Starting Non-Language Environment Debug Tool under CICS	61
Passing run-time parameters into the non-Language Environment debug session on startup	61

Chapter 14. Preparing an IMS program 63

Creating setup file for your IMS program by using Debug Tool Utilities	64
Setting up the run-time options for your IMS Version 8 TM program by using Debug Tool Utilities	64
Linking IMS programs for debugging	65

Part 3. Starting Debug Tool. 67

Chapter 15. Starting Debug Tool from the Debug Tool Utilities 69

Creating the setup file	69
Editing an existing setup file	69
Copying information into a setup file from an existing JCL	70
Entering file allocation statements, run-time options, and program parameters	70
Saving your setup file	72
Starting your program.	72

Chapter 16. Starting Debug Tool by using the TEST run-time option 73

Special considerations while using the TEST run-time option	73
Defining TEST suboptions in your program	73
Suboptions and NOTEST	74
Implicit breakpoints	74
Primary commands file and USE file	74
Running in batch mode	74
Starting Debug Tool at different points	74
Session log	75
Precedence of Language Environment run-time options	75
Example: TEST run-time options	76
Specifying additional run-time options with COBOL II and PL/I programs	77
Specifying the STORAGE run-time option	77
Specifying the TRAP(ON) run-time option	77
Specifying TEST run-time option with #pragma runopts in C and C++	78

Chapter 17. Starting Debug Tool from a program 79

Starting Debug Tool with CEETEST	79
Usage notes	81
Example: using CEETEST to start Debug Tool from C/C++	81
Example: using CEETEST to start Debug Tool from COBOL.	83
Example: using CEETEST to start Debug Tool from PL/I.	84
Starting Debug Tool with PLITEST	85
Starting Debug Tool with the __ctest() function	86

Chapter 18. Starting Debug Tool for batch or TSO programs 89

Programs that start in Language Environment.	89
Starting Debug Tool in batch mode	91
Programs that start outside of Language Environment	92
Passing parameters to EQANMDBG	93

Chapter 19. Starting Debug Tool under CICS. 95

Choosing a debug mode	95
Methods for starting Debug Tool under CICS	96
Starting Debug Tool by using DTCN	97
Starting Debug Tool by using CADP	98
Starting Debug Tool by using CEEUOPT	98
Starting Debug Tool by using compiler directives	99
Starting Debug Tool under CICS by using CEDF	99

Chapter 20. Starting a full-screen debug session 101

Chapter 21. Starting Debug Tool in other environments. 103

Starting a debugging session in full-screen mode through a VTAM terminal	103
Starting Debug Tool from DB2 stored procedures: troubleshooting.	103

Part 4. Debugging your programs in full-screen mode 105

Chapter 22. Using full-screen mode:

overview	107
Debug Tool session panel	107
Session panel header	108
Source window	110
Monitor window	111
Log window.	112
Creating a preferences file	113
Displaying the source.	113
Entering commands on the session panel	114
Order in which Debug Tool accepts commands from the session panel	115
Using the session panel command line	115
Issuing system commands	116
Using prefix commands on specific lines or statements	116
Using commands that are sensitive to the cursor position	117
Using Program Function (PF) keys to enter commands	117
Initial PF key settings.	117
Retrieving previous commands	118
Retrieving commands from the Log and Source windows	118
Navigating through Debug Tool session panel windows	119
Moving the cursor between windows	119
Scrolling the windows	119
Scrolling to a particular line number.	120
Finding a string in a window	120
Changing which source file appears in the Source window.	120
Displaying the line at which execution halted	121
Creating a commands file	121
Recording your debug session in a log file	122
Creating the log file	122
Recording how many times each source line runs	123
Recording the breakpoints encountered.	124
Setting breakpoints to halt your program at a line	124
Stepping through or running your program	124
Recording and replaying statements.	124
Displaying and monitoring the value of a variable	127
One-time display of the value of variables.	128
Monitoring the value of variables	128
Displaying values in hexadecimal format	129
Monitoring the value of variables in hexadecimal format	130
Modifying variables	130
Opening and closing the Monitor window.	131
Managing file allocations	131

Displaying error numbers for messages in the Log window	133
Finding a renamed source, listing, or separate debug file	133
Requesting an attention interrupt during interactive sessions	134
Ending a full-screen debug session	134

Chapter 23. Debugging a COBOL

program in full-screen mode 137

Example: sample COBOL program for debugging	137
Halting when certain routines are called in COBOL	140
Modifying the value of a COBOL variable.	141
Halting on a COBOL line only if a condition is true	142
Debugging COBOL when only a few parts are compiled with TEST	143
Capturing COBOL I/O to the system console.	143
Displaying raw storage in COBOL	144
Getting a COBOL routine traceback	144
Tracing the run-time path for COBOL code compiled with TEST	144
Generating a COBOL run-time paragraph trace	145
Finding unexpected storage overwrite errors in COBOL	146
Halting before calling an invalid program in COBOL	146

Chapter 24. Debugging an OS/VS

COBOL program in full-screen mode . 149

Example: sample OS/VS COBOL program for debugging	149
Defining a compilation unit as OS/VS COBOL and loading debug information	151
Defining a compilation unit in a different load module as OS/VS COBOL	152
Halting when certain OS/VS COBOL programs are called	152
Displaying and modifying the value of OS/VS COBOL variables or storage	152
Halting on a line in OS/VS COBOL only if a condition is true	153
Debugging OS/VS COBOL when debug information is only available for a few parts	153
Getting an OS/VS COBOL program traceback	153
Finding unexpected storage overwrite errors in OS/VS COBOL.	154

Chapter 25. Debugging a PL/I program

in full-screen mode 155

Example: sample PL/I program for debugging	155
Halting when certain PL/I functions are called	158
Modifying the value of a PL/I variable.	158
Halting on a PL/I line only if a condition is true	159
Debugging PL/I when only a few parts are compiled with TEST	159
Displaying raw storage in PL/I	160
Getting a PL/I function traceback	160
Tracing the run-time path for PL/I code compiled with TEST	161

Finding unexpected storage overwrite errors in PL/I	162
Halting before calling an undefined program in PL/I	162

Chapter 26. Debugging a C program in full-screen mode 163

Example: sample C program for debugging	163
Halting when certain functions are called in C	166
Modifying the value of a C variable	166
Halting on a line in C only if a condition is true	167
Debugging C when only a few parts are compiled with TEST	168
Capturing C output to stdout	168
Calling a C function from Debug Tool	168
Displaying raw storage in C	169
Debugging a C DLL	169
Getting a function traceback in C	169
Tracing the run-time path for C code compiled with TEST	170
Finding unexpected storage overwrite errors in C	170
Finding uninitialized storage errors in C	171
Halting before calling a NULL C function	172

Chapter 27. Debugging a C++ program in full-screen mode 173

Example: sample C++ program for debugging	173
Halting when certain functions are called in C++	177
Modifying the value of a C++ variable	177
Halting on a line in C++ only if a condition is true	178
Viewing and modifying data members of the this pointer in C++	179
Debugging C++ when only a few parts are compiled with TEST	179
Capturing C++ output to stdout	180
Calling a C++ function from Debug Tool	180
Displaying raw storage in C++	180
Debugging a C++ DLL	180
Getting a function traceback in C++.	181
Tracing the run-time path for C++ code compiled with TEST	181
Finding unexpected storage overwrite errors in C++	182
Finding uninitialized storage errors in C++	182
Halting before calling a NULL C++ function	183

Chapter 28. Debugging an assembler program in full-screen mode 185

Example: sample assembler program for debugging	185
Defining a compilation unit as assembler and loading debug data	188
Deferred LDDs	189
Re-appearance of an assembler CU	189
Multiple compilation units in a single assembly	189
Halting when certain assembler routines are called	190
Displaying and modifying the value of assembler variables or storage	190
Converting a hexadecimal address to a symbolic address	191

Halting on a line in assembler only if a condition is true	191
Getting an assembler routine traceback	191
Finding unexpected storage overwrite errors in assembler	192

Chapter 29. Customizing your full-screen session 193

Defining PF keys	193
Defining a symbol for commands or other strings	194
Customizing the layout of windows on the session panel	194
Opening and closing session panel windows	195
Resizing session panel windows	195
Zooming a window to occupy the whole screen	196
Customizing session panel colors	196
Customizing profile settings	197
Saving customized settings in a preferences files	199

Part 5. Debugging your programs by using Debug Tool commands . 201

Chapter 30. Entering Debug Tool commands 203

Using uppercase, lowercase, and DBCS in Debug Tool commands	203
DBCS	203
Character case and DBCS in C and C++	204
Character case in COBOL and PL/I	204
Abbreviating Debug Tool keywords	204
Entering multiline commands in full-screen and line mode	205
Entering multiline commands in a command file	205
Entering multiline commands without continuation	206
Using blanks in Debug Tool commands	206
Entering comments in Debug Tool commands	206
Using constants in Debug Tool commands	207
Getting online help for Debug Tool command syntax	207

Chapter 31. Debugging COBOL programs 209

Format for a COBOL source listing and debug file	209
Debug Tool commands that resemble COBOL statements	209
COBOL command format	210
COBOL compiler options in effect for Debug Tool commands	210
COBOL reserved keywords	211
Using COBOL variables with Debug Tool	211
Accessing COBOL variables	211
Assigning values to COBOL variables	211
Example: assigning values to COBOL variables	212
Displaying values of COBOL variables	213
Using DBCS characters in COBOL	213
%PATHCODE values for COBOL	214
Declaring session variables in COBOL	215
Debug Tool evaluation of COBOL expressions	215

Displaying the results of COBOL expression evaluation	216
Using constants in COBOL expressions	216
Using Debug Tool functions with COBOL	217
Using %HEX with COBOL	217
Using the %STORAGE function with COBOL	217
Qualifying variables and changing the point of view in COBOL	217
Qualifying variables in COBOL	218
Changing the point of view in COBOL	219
Considerations when debugging a COBOL class	219
Debugging VS COBOL II programs	220
Finding the listing of a VS COBOL II program	220

Chapter 32. Debugging an OS/VS COBOL program 223

Loading an OS/VS COBOL program's debug information	223
Debug Tool session panel while debugging an OS/VS COBOL program	224
Restrictions for debugging an OS/VS COBOL program	225
%PATHCODE values for OS/VS COBOL programs	225
Restrictions for debugging non-Language Environment programs	225

Chapter 33. Debugging PL/I programs 227

Debug Tool subset of PL/I commands	227
PL/I language statements	227
%PATHCODE values for PL/I	228
PL/I conditions and condition handling	229
Entering commands in PL/I DBCS freeform format	230
Initializing Debug Tool when TEST(ERROR, ...) run-time option is in effect	230
Debug Tool enhancements to LIST STORAGE PL/I command	230
PL/I support for Debug Tool session variables	230
Accessing PL/I program variables	231
Accessing PL/I structures	231
Debug Tool evaluation of PL/I expressions	232
Supported PL/I built-in functions	232
Using SET WARNING PL/I command with built-in functions	234
Unsupported PL/I language elements	234
Debugging OS PL/I programs	234
Restrictions while debugging Enterprise PL/I programs	235

Chapter 34. Debugging C and C++ programs 237

Debug Tool commands that resemble C and C++ commands	237
Using C and C++ variables with Debug Tool	238
Accessing C and C++ program variables	238
Displaying values of C and C++ variables or expressions	238
Assigning values to C and C++ variables	239
%PATHCODE values for C and C++	240
Declaring session variables with C and C++	240
C and C++ expressions	241

Calling C and C++ functions from Debug Tool	242
C reserved keywords	243
C operators and operands	243
Language Environment conditions and their C and C++ equivalents	244
Debug Tool evaluation of C and C++ expressions	245
Intercepting files when debugging C and C++ programs	246
Scope of objects in C and C++	248
Storage classes in C and C++	249
Blocks and block identifiers for C	250
Blocks and block identifiers for C++	250
Example: referencing variables and setting breakpoints in C and C++ blocks	251
Scope and visibility of objects	251
Blocks and block identifiers	251
Displaying environmental information	252
Qualifying variables and changing the point of view in C and C++	252
Qualifying variables in C and C++	253
Changing the point of view in C and C++	253
Example: using qualification in C	254
Stepping through C++ programs	255
Setting breakpoints in C++	255
Setting breakpoints in C++ using AT ENTRY/EXIT	255
Setting breakpoints in C++ using AT CALL	256
Examining C++ objects	257
Example: displaying attributes of C++ objects	257
Monitoring storage in C++	258
Example: monitoring and modifying registers and storage in C	258

Chapter 35. Debugging an assembler program 261

The SET ASSEMBLER and SET DISASSEMBLY commands	261
Loading an assembler program's debug information	261
Debug Tool session panel while debugging an assembler program	262
%PATHCODE values for assembler programs	263
Restrictions for debugging an assembler program	265
Restrictions for debugging a Language Environment assembler MAIN program	266
Restrictions on setting breakpoints in the prologue of Language Environment assembler programs	266
Restrictions for debugging non-Language Environment programs	266
Restrictions for debugging self-modifying code	266

Chapter 36. Debugging a disassembled program 269

The SET ASSEMBLER and SET DISASSEMBLY commands	269
Capabilities of the disassembly view	269
Starting the disassembly view	270
The disassembly view	270
Performing single-step operations	271

Setting breakpoints	271
Restrictions for debugging self-modifying code	271
Displaying and modifying registers	272
Displaying and modifying storage	272
Changing the program displayed in the disassembly view	272
Restrictions for the disassembly view	272

Part 6. Debugging in different environments 275

Chapter 37. Debugging DB2 programs 277

Debugging DB2 programs in batch mode	277
Debugging DB2 programs in full-screen mode	277

Chapter 38. Debugging DB2 stored procedures 279

Resolving some common problems	279
--	-----

Chapter 39. Debugging IMS programs 281

Debugging IMS programs in interactive mode	281
Debugging IMS programs in batch mode	282

Chapter 40. Debugging CICS programs 283

Debug modes under CICS	284
Preventing Debug Tool from stopping at EXEC CICS RETURN	284
Saving settings while debugging a pseudo-conversational program	284
Saving and restoring breakpoints (DTCN only)	285
Restrictions when debugging under CICS	285
Accessing CICS resources during a debugging session	285

Chapter 41. Debugging ISPF applications 287

Chapter 42. Debugging programs in a production environment. 289

Fine-tuning your programs with Debug Tool	289
Removing hooks	289
Removing statement and symbol tables.	290
Debugging without hooks, statement tables, and symbol tables	290
Debugging optimized COBOL programs	291

Chapter 43. Debugging UNIX System Services programs 293

Debugging MVS POSIX programs	293
--	-----

Chapter 44. Debugging non-Language Environment programs 295

Debugging exclusively non-Language Environment programs.	295
Debugging MVS batch or TSO non-Language Environment initial programs	295

Debugging CICS non-Language Environment assembler or OS/VS COBOL initial programs	295
--	-----

Part 7. Debugging complex applications 297

Chapter 45. Debugging multilanguage applications 299

Debug Tool evaluation of HLL expressions	299
Debug Tool interpretation of HLL variables and constants	300
HLL variables	300
HLL constants	300
Debug Tool commands that resemble HLL commands	300
Qualifying variables and changing the point of view	301
Qualifying variables	301
Changing the point of view	303
Handling conditions and exceptions in Debug Tool	303
Handling conditions in Debug Tool	304
Handling exceptions within expressions (C and C++ and PL/I only)	305
Debugging multilanguage applications	305
Debugging an application fully supported by Language Environment	306
Using session variables across different languages	306
Coexistence with other debuggers	308
Coexistence with unsupported HLL modules.	308

Chapter 46. Debugging multithreading programs 309

Restrictions when debugging multithreading applications	309
--	-----

Chapter 47. Debugging across multiple processes and enclaves 311

Starting Debug Tool within an enclave	311
Viewing Debug Tool windows across multiple enclaves	312
Ending a Debug Tool session within multiple enclaves	312
Using Debug Tool commands within multiple enclaves	312

Chapter 48. Debugging a multiple-enclave interlanguage communication (ILC) application 317

Part 8. Appendixes 319

Appendix A. Data sets used by Debug Tool 321

Appendix B. How does Debug Tool locate debug information and source or listing files? 325

How does Debug Tool locate source and listing files?	325
How does Debug Tool locate COBOL side files?	326
How does Debug Tool locate EQALANGX files	326

Appendix C. Examples: Preparing programs and modifying setup files with Debug Tool Utilities 327

Creating personal data sets	327
Starting Debug Tool Utilities	328
Compiling or assembling your program by using Debug Tool Utilities	328
Modifying and using a setup file	331
Run the program in foreground	331
Run the program in batch	332

Appendix D. Notes on debugging in batch mode 333

Appendix E. Notes on debugging in remote debug mode 335

Debug Tool commands supported in remote debug mode	336
Tip on monitoring variables in optimized COBOL program	336

Appendix F. Syntax of the TEST Compiler option 337

Syntax for the C TEST compiler option	338
Syntax for the C++ TEST compiler option	339
Syntax for the COBOL TEST compiler option	340
Syntax for the PL/I and Enterprise PL/I TEST compiler options	343

Appendix G. Debug Tool Load Module Analyzer 347

Choosing a starting method	347
Starting the Load Module Analyzer by using JCL	347
Starting the Load Module Analyzer by using Debug Tool Utilities	347
Description of the JCL	347
Description of DD names	347
Description of parameters	348
Description of EQASYSPP file format	349
Description of EQAPGMNM file format	350
Description of program output	351
Description of output contents	351
Example: Output for an OS/VS COBOL load module	352

Appendix H. Accessibility 353

Using assistive technologies	353
Keyboard navigation of the user interface	353
Accessibility of this document	353

Notices 355

Copyright license	356
Programming interface information	356
Trademarks and service marks	356

Bibliography. 357

Debug Tool publications.	357
High level language publications.	357
Related publications	357
Softcopy publications.	358

Glossary 359

Index 365

About this document

Debug Tool combines the richness of the z/OS[®] and OS/390[®] environments with the power of Language Environment[®] to provide a debugger for programmers to isolate and fix their program bugs and test their applications. Debug Tool gives you the capability of testing programs in batch, using a nonprogrammable terminal in full-screen mode, or using a workstation interface to remotely debug your programs.

The Debug Tool Utilities and Advanced Functions Coverage Utility is referred to throughout this document as the Debug Tool Coverage Utility or Coverage Utility.

Who might use this document

This document is intended for programmers using Debug Tool to debug high-level languages (HLLs) with Language Environment and assembler programs either with or without Language Environment. Throughout this document, the HLLs are referred to as C, C++, COBOL, and PL/I.

The following operating systems and subsystems are supported:

- z/OS and OS/390
 - CICS[®]
 - DB2[®]
 - IMS[™]
 - JES batch
 - TSO
 - UNIX[®] System Services in remote debug mode or full-screen mode through a VTAM terminal only
 - WebSphere[®] in remote debug mode or full-screen mode through a VTAM terminal only

To use this document and debug a program written in one of the supported languages, you need to know how to write, compile, and run such a program.

Accessing z/OS licensed documents on the Internet

z/OS licensed documentation is available on the Internet in PDF format at the IBM[®] Resource Link[™] Web site at:

<http://www.ibm.com/servers/resourceLink>

Licensed documents are available only to customers with a z/OS license. Access to these documents requires an IBM Resource Link user ID and password, and a key code. With your z/OS order you received a Memo to Licensees, (GI10-0671), that includes this key code.

To obtain your IBM Resource Link user ID and password, log on to:

<http://www.ibm.com/servers/resourceLink>

To register for access to the z/OS licensed documents:

1. Sign in to Resource Link using your Resource Link user ID and password.
2. Select **User Profiles** located on the left-hand navigation bar.

Note: You cannot access the z/OS licensed documents unless you have registered for access to them and received an e-mail confirmation informing you that your request has been processed.

Printed licensed documents are not available from IBM.

You can use the PDF format on either **z/OS Licensed Product Library CD-ROM** or IBM Resource Link to print licensed documents.

Using LookAt to look up message explanations

LookAt is an online facility that lets you look up explanations for most of the IBM messages you encounter, as well as for some system abends and codes. Using LookAt to find information is faster than a conventional search because in most cases LookAt goes directly to the message explanation.

You can use LookAt from the following locations to find IBM message explanations for z/OS elements and features, z/VM[®], VSE/ESA[™], and Clusters for AIX[®] and Linux[™]:

- The Internet. You can access IBM message explanations directly from the LookAt Web site at <http://www.ibm.com/eserver/zseries/zos/bkserv/lookat/>.
- Your z/OS TSO/E host system. You can install code on your z/OS or z/OS.e systems to access IBM message explanations, using LookAt from a TSO/E command line (for example, TSO/E prompt, ISPF, or z/OS UNIX System Services running OMVS).
- Your Microsoft[®] Windows[®] workstation. You can install code to access IBM message explanations on the *z/OS Collection* (SK3T-4269), using LookAt from a Microsoft Windows command prompt (also known as the DOS command line).
- Your wireless handheld device. You can use the LookAt Mobile Edition with a handheld device that has wireless access and an Internet browser (for example, Internet Explorer for Pocket PCs, Blazer, or Eudora for Palm OS, or Opera for Linux handheld devices). Link to the LookAt Mobile Edition from the LookAt Web site.

You can obtain code to install LookAt on your host system or Microsoft Windows workstation from a disk on your *z/OS Collection* (SK3T-4269), or from the LookAt Web site (click **Download**, and select the platform, release, collection, and location that suit your needs). More information is available in the LOOKAT.ME files available during the download process.

How this document is organized

This document is divided into areas of similar information for easy retrieval of appropriate information. The following list describes how the information is grouped:

- Part 1 groups together introductory information about Debug Tool. The following list describes each chapter:
 - Chapter 1 introduces Debug Tool and describes some of its features.
 - Chapter 2 introduces Debug Tool Utilities and Advanced Functions and describes some of its features.
 - Chapter 3 provides instructions on how to use full-screen mode to debug a program.
- Part 2 groups together information about how to prepare programs for debugging. The following list describes each chapter:

- Chapter 4 describes some of the preliminary planning and resource actions to take when you prepare your programs.
- Chapter 5 describes how to prepare a COBOL program.
- Chapter 6 describes how to prepare an OS/VS COBOL program.
- Chapter 7 describes how to prepare a PL/I programs.
- Chapter 8 describes how to prepare a C program.
- Chapter 9 describes how to prepare a C++ program
- Chapter 10 describes how to prepare an assembler program.
- Chapter 11 describes how to prepare a DB2 program.
- Chapter 12 describes how to prepare a DB2 stored procedures program.
- Chapter 13 describes how to prepare a CICS program.
- Chapter 14 describes how to prepare an IMS program.
- Part 3 groups together information that describes the different methods you can use to start Debug Tool. The following list describes each chapter:
 - Chapter 15 describes how to start Debug Tool from Debug Tool Utilities.
 - Chapter 16 describes how to start Debug Tool Utilities by using the TEST run-time option.
 - Chapter 17 describes how to start Debug Tool from a program.
 - Chapter 18 describes how to start Debug Tool for your batch or TSO programs.
 - Chapter 19 describes how to start Debug Tool from CICS programs.
 - Chapter 20 describes how to start Debug Tool in full-screen mode.
 - Chapter 21 describes how to start Debug Tool in full-screen mode through a VTAM[®] terminal. This chapter also describes some tips to starting Debug Tool from a stored procedure.
- Part 4 groups together information about how to debug a program in full-screen mode and provides an example of how to debug a C, COBOL, and PL/I program in full-screen mode. The following list describes each chapter:
 - Chapter 22 provides overview information about full-screen mode.
 - Chapter 23 provides a sample COBOL program to describe how to debug it in full-screen mode.
 - Chapter 24 provides a sample OS/VS COBOL program to describe how to debug it in full-screen mode.
 - Chapter 25 provides a sample PL/I program to describe how to debug it in full-screen mode.
 - Chapter 26 provides a sample C program to describe how to debug it in full-screen mode.
 - Chapter 27 provides a sample C++ program to describe how to debug it in full-screen mode.
 - Chapter 28 provides a sample assembler program to describe how to debug it in full-screen mode.
 - Chapter 29 describes how to modify the appearance of a full-screen mode debugging session.
- Part 5 groups together information about how to enter and use Debug Tool commands.
 - Chapter 30 provides information about entering mixed case commands, using DBCS characters, abbreviating commands, entering multiline commands, and entering comments.

- Chapter 31 describes how to use Debug Tool commands to debug COBOL programs.
- Chapter 32 describes how to use Debug Tool commands to debug OS/VS COBOL programs.
- Chapter 33 describes how to use Debug Tool commands to debug PL/I programs.
- Chapter 34 describes some of the restrictions you must know about while you debug Enterprise PL/I programs.
- Chapter 35 describes how to use Debug Tool commands to debug C or C++ programs.
- Chapter 36 describes how to use Debug Tool commands to debug assembler programs.
- Chapter 37 describes how to use Debug Tool commands to debug disassembly programs.
- Part 6 groups together information about debugging DB2, DB2 stored procedures, IMS, CICS, ISPF, UNIX System Services, and production-level programs.
 - Chapter 38 describes how to debug a DB2 program.
 - Chapter 39 describes how to debug a DB2 stored procedure.
 - Chapter 40 describes how to debug an IMS program.
 - Chapter 41 describes how to debug a CICS program.
 - Chapter 42 describes how to debug an ISPF program.
 - Chapter 43 describes how to debug a production-level program.
 - Chapter 44 describes how to debug a program running in the UNIX System Services shell.
 - Chapter 45 describes how to debug programs that do not start or run in Language Environment.
- Part 7 groups together information about how to debug programs written in multiple language or running in multiple processes.
 - Chapter 46 describes how to debug a program written in multiple languages.
 - Chapter 47 describes the restrictions when you debug a multithreaded program.
 - Chapter 48 describes how to debug a program that runs across multiple processes and enclaves.
 - Chapter 49 describes how to debug a multiple-enclave interlanguage communication (ILC) application.
- Part 8 groups together appendices. The following list describes each appendix:
 - Appendix A describes the data sets that Debug Tool uses to retrieve and store information.
 - Appendix B provides an example that guides you through the process of preparing a sample program and modifying existing setup files by using Debug Tool Utilities.
 - Appendix C describes the process Debug Tool uses to locate source, listing, or side files.
 - Appendix D provides information about debugging a program in batch mode.
 - Appendix E provides information about debugging a program in remote debug mode.
 - Appendix F describes the syntax of the TEST compiler option.

- Appendix G describes how to use Load Module Analyzer, a stand-alone program that is part of Debug Tool Utilities and Advanced Functions.
- Appendix H describes the features and tools available to people with physical disabilities that help them use Debug Tool and Debug Tool documents.

The last several chapters list notices, bibliography, and glossary of terms.

Terms used in this document

Because of differing terminology among the various programming languages supported by Debug Tool, as well as differing terminology between platforms, a group of common terms has been established. The table below lists these terms and their equivalency in each language.

Debug Tool term	C and C++ equivalent	COBOL equivalent	PL/I equivalent	assembler
Compile unit	C and C++ source file	Program or class	Program (or PL/I source file for Enterprise PL/I)	CSECT
Block	Function or compound statement	Program, nested program, method or PERFORM group of statements	Block	CSECT
Label	Label	Paragraph name or section name	Label	Label

Debug Tool provides facilities that apply only to programs compiled with specific levels of compilers. Because of this, *Debug Tool for z/OS User's Guide* uses the following terms:

assembler

Refers to assembler programs with debug information assembled by using the High Level Assembler (HLASM).

COBOL

Refers to the all COBOL compilers and dialects supported by Debug Tool except OS/VS COBOL.

disassembly or disassembled

Refers to high-level language programs compiled without debug information or assembler programs without debug information. The debugging support Debug Tool provides for these programs is through the disassembly view.

Enterprise PL/I

Refers to the Enterprise PL/I for z/OS and OS/390 and the VisualAge® PL/I for OS/390 compilers.

OS/VS COBOL

Refers to COBOL programs compiled using the IBM OS/VS COBOL compiler.

As you read through the information in this document, remember that OS/VS COBOL programs are non-Language Environment programs, even though you might have used Language Environment libraries to link and run your program. Please read the information regarding non-Language

Environment programs for instructions on how to start Debug Tool and debug OS/VS COBOL programs, unless OS/VS COBOL-specific information is provided.

How to read syntax diagrams

This section describes how to read syntax diagrams. It defines syntax diagram symbols, items that may be contained within the diagrams (keywords, variables, delimiters, operators, fragment references, operands) and provides syntax examples that contain these items.

Syntax diagrams pictorially display the order and parts (options and arguments) that comprise a command statement. They are read from left to right and from top to bottom, following the main path of the horizontal line.

Symbols

The following symbols may be displayed in syntax diagrams:

Symbol	Definition
▶—	Indicates the beginning of the syntax diagram.
—▶	Indicates that the syntax diagram is continued to the next line.
▶—	Indicates that the syntax is continued from the previous line.
—▶▶	Indicates the end of the syntax diagram.

Syntax items

Syntax diagrams contain many different items. Syntax items include:

- Keywords - a command name or any other literal information.
- Variables - variables are italicized, appear in lowercase and represent the name of values you can supply.
- Delimiters - delimiters indicate the start or end of keywords, variables, or operators. For example, a left parenthesis is a delimiter.
- Operators - operators include add (+), subtract (-), multiply (*), divide (/), equal (=), and other mathematical operations that may need to be performed.
- Fragment references - a part of a syntax diagram, separated from the diagram to show greater detail.
- Separators - a separator separates keywords, variables or operators. For example, a comma (,) is a separator.









Keywords, variables, and operators may be displayed as required, optional, or default. Fragments, separators, and delimiters may be displayed as required or optional.

Item type	Definition
Required	Required items are displayed on the main path of the horizontal line.
Optional	Optional items are displayed below the main path of the horizontal line.
Default	Default items are displayed above the main path of the horizontal line.

Syntax examples

The following table provides syntax examples.

Table 1. Syntax examples

Item	Syntax example
Required item.	
Required items appear on the main path of the horizontal line. You must specify these items.	
Required choice.	
A required choice (two or more items) appears in a vertical stack on the main path of the horizontal line. You must choose one of the items in the stack.	
Optional item.	
Optional items appear below the main path of the horizontal line.	
Optional choice.	
An optional choice (two or more items) appears in a vertical stack below the main path of the horizontal line. You may choose one of the items in the stack.	
Default.	
Default items appear above the main path of the horizontal line. The remaining items (required or optional) appear on (required) or below (optional) the main path of the horizontal line. The following example displays a default with optional items.	
Variable.	
Variables appear in lowercase italics. They represent names or values.	
Repeatable item.	
An arrow returning to the left above the main path of the horizontal line indicates an item that can be repeated.	
A character within the arrow means you must separate repeated items with that character.	
An arrow returning to the left above a group of repeatable items indicates that one of the items can be selected, or a single item can be repeated.	
Fragment.	
The — fragment — symbol indicates that a labelled group is described below the main syntax diagram. Syntax is occasionally broken into fragments if the inclusion of the fragment would overly complicate the main syntax diagram.	fragment: 

How to send your comments

Your feedback is important in helping us to provide accurate, high-quality information. If you have comments about this document or any other Debug Tool documentation, contact us in one of these ways:

- Use the Online Readers' Comment Form at www.ibm.com/software/awdtools/rcf/. Be sure to include the name of the document, the publication number of the document, the version of Debug Tool, and, if applicable, the specific location (for example, page number) of the text that you are commenting on.
- Fill out the Readers' Comment Form at the back of this document, and return it by mail or give it to an IBM representative. If the form has been removed, address your comments to:

IBM Corporation
H150/090
555 Bailey Avenue
San Jose, CA 95141-1003
USA

- Fax your comments to this U.S. number: (800)426-7773.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

Summary of changes

This section lists the key changes made to Debug Tool for z/OS and Debug Tool Utilities and Advanced Functions for z/OS that affect this document.

Debug Tool for z/OS Version 5.1 with PTF for APAR PK07204 applied

An appendix describing the Load Module Analyzer has been added. The Debug Tool Load Module Analyzer analyzes MVS load modules or program objects to determine the language translator (compiler or assembler) used to generate the object for each CSECT. To use the Load Module Analyzer, you must purchase and install Debug Tool Utilities and Advanced Functions Version 5.1 (5655-M19) with the PTF for APAR PK07204.

Debug Tool for z/OS Version 5.1 with PTF for APAR PK00675 applied

- The requirement for Enterprise PL/I programs to link-edit EQADCCXT into CICS program has changed. See Chapter 13, “Preparing a CICS program,” on page 55 for more information.
- Site control of DTCN behaviour.

Debug Tool now provides a way to require that users specify certain DTCN fields. The site administrator can use the DTCNFORCE options in EQAOPTS to specify which DTCN fields must be completed.
- The following enhancements related to CICS programs have been added:
 - A new CICS PLTPI program, EQA0CPLT, is provided, which does the following actions:
 - Activate support for programs that run in multi-region environments.
 - Activate support for Enterprise PL/I for z/OS Version 3 Release 4 programs for CADP users.
 - Activate Debug Tool screen stacking exits during CICS startup.
 - Activate some exits, during CICS startup, that enable you to debug non-Language Environment programs. Activating these exits replaces the need to run the CICS PLTPI program EQANCPLT.
 - New customizations in EQAOPTS are available to require DTCN users to specify some or all the of the resource types.
- Miscellaneous technical corrections.

Debug Tool for z/OS Version 5.1 with PTF for APAR PQ94401 applied

- Support for OS/VS COBOL.

The terminology for COBOL-related information has changed. The term COBOL applies to all programs compiled with supported COBOL compilers and dialects except for OS/VS COBOL. The term OS/VS COBOL applies to programs compiled with the IBM OS/VS COBOL compiler.
- Global preferences file.

Information has been added to describe how to use global preferences files, which can be used to specify settings for Debug Tool sessions started throughout your site.

- Clarification that Debug Tool does not support debugging of optimized C, C++, PL/I, and older COBOL programs.
- Site or user control of SVC screening.
For sites that have products that use SVC screening, Debug Tool provides a mechanism to enable or disable SVC screening and override current settings.
- Miscellaneous technical corrections.

Debug Tool for z/OS Version 5.1

- Improved performance when you debug C, C++, and PL/I programs.
Debug Tool can now use the Dynamic Debug facility to implement breakpoints while you debug C, C++, and PL/I programs. Hooks inserted by the compiler are still required. The use of the Dynamic Debug facility can help improve performance of the programs that are running under control of Debug Tool.
- Support for debugging assembler programs that do not run in Language Environment or are not Language Environment-enabled.
- Debug Tool provides support for more commands that you can use in remote debug mode. For example, the SET AUTOMONITOR command can now be used to automonitor variables through the Compiled Language Debugger component of WebSphere Studio Enterprise Developer in the same way you can automonitor variables when you debug in full-screen mode.
- The AT TERMINATION breakpoints are no longer set by default.
- You can now automonitor variables in assembler programs and the disassembly view.

Part 1. Getting started with Debug Tool

Chapter 1. Debug Tool: overview

Debug Tool helps you test programs and examine, monitor, and control the execution of programs written in assembler, C, C++, COBOL, or PL/I on a z/OS or OS/390 system. Your applications can include other languages; Debug Tool provides a disassembly view that lets you debug, at the machine code level, those portions of your application. However, in the disassembly view, your debugging capabilities are limited. Table 2 and Table 3 on page 4 map out the combinations of compilers and subsystems that Debug Tool supports.

You can use Debug Tool to debug your programs in batch mode, interactively in full-screen mode, or in remote debug mode.

Table 2 maps out the Debug Tool interfaces and compilers or assemblers each interface supports.

Table 2. Debug Tool interface type by compiler or assembler

Compiler or assembler	Batch mode	Full-screen mode	Remote debug mode
VS COBOL II Version 1 Release 3 and Version 1 Release 4 (with limitations)	X	X	X
AD/Cycle COBOL/370 Version 1 Release 1	X	X	
OS/VS COBOL, Version 1 Release 2.4 (with limitations)	X	X	
COBOL for MVS & VM	X	X	X
COBOL for OS/390 & VM	X	X	X
Enterprise COBOL for z/OS and OS/390	X	X	X
OS PL/I Version 2 Release 1, Version 2 Release 2, and Version 2 Release 3 (with limitations)	X	X	
PL/I for MVS & VM	X	X	
Enterprise PL/I	X	X	X
AD/Cycle C/370 Version 1 Release 2	X	X	
C/C++ for MVS/ESA Version 3 Release 2	X	X	
C/C++ feature of OS/390 Version 1 Release 3 and earlier	X	X	
C/C++ feature of OS/390 Version 2 Release 10 and later	X	X	X
C/C++ feature of z/OS	X	X	X
IBM High Level Assembler (HLASM), Version 1 Release 4	X	X	X

Table 3 on page 4 maps out the Debug Tool interfaces and subsystems each interface supports.

Table 3. Debug Tool interface type by subsystem

Subsystem	Batch mode	Full-screen mode	Remote mode
TSO	X	X	X
JES batch	X	X*	X
UNIX System Services		X*	X
CICS	X	X	X
DB2	X	X	X
DB2 stored procedures		X*	X
IMS (TM and DB) with BTS TSO foreground		X	X
IMS (TM and DB) with BTS batch	X	X*	X
IMS without BTS IMS DB batch	X	X*	X
IMS without BTS IMS TM		X*	X

*Support is for full-screen mode through a VTAM terminal only.

Refer to the following sections for more information related to the material discussed in this section.

Related concepts

“Debug Tool interfaces”

Related tasks

Chapter 4, “Planning your debug session and collecting resources,” on page 21

Chapter 22, “Using full-screen mode: overview,” on page 107

Related references

Debug Tool for z/OS Reference and Messages

Debug Tool interfaces

The terms *full-screen mode*, *batch mode*, and *remote debug mode* identify the types of debugging interfaces that Debug Tool provides.

Full-screen mode

Debug Tool provides an interactive full-screen interface on a 3270 device, with debugging information displayed in three windows:

- A Source window in which to view your program source or listing
- A Log window, which records commands and other interactions between Debug Tool and your program
- A Monitor window in which to monitor changes in your program

You can debug all languages supported by Debug Tool in full-screen mode.

You can debug non-TSO and non-CICS programs in full-screen mode by using the full-screen mode through a VTAM terminal facility. For example, you can debug a COBOL batch job running in MVS/JES, a DB2 Stored Procedure, an IMS transaction running on a IMS MPP region, or an application running in UNIX System Services. Contact your system administrator to determine how to access a terminal capable of using the full-screen mode through a VTAM terminal facility on your system.

You can debug CICS programs in several different modes, which are described in “Debug modes under CICS” on page 284.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Debug Tool for z/OS Customization Guide

Batch mode

You can use Debug Tool command files to predefine series of Debug Tool commands to be performed on a running batch application. Neither terminal input nor user interaction is available for batch debugging of a batch application. The results of the debugging session are saved to a log, which you can review at a later time.

Remote debug mode

In remote debug mode, the host application starts Debug Tool, which uses a TCP/IP connection to communicate with a remote debugger on your Windows workstation.

Debug Tool, in conjunction with a remote debugger, provides users with the ability to debug host programs, including batch programs, through a graphical user interface (GUI) on the workstation. The following remote debuggers are available:

- Compiled Language Debugger component of WebSphere Studio Enterprise Developer

This remote debugger is the recommended choice as it offers more functionality over the IBM Distributed Debugger. For more information about the commands that Debug Tool supports with this remote debugger, see Appendix E, “Notes on debugging in remote debug mode,” on page 335. For more information about software requirements for this remote debugger, see *Program Directory for Debug Tool for z/OS*.

- IBM Distributed Debugger

This remote debugger is available through the following products:

- OS/390 C/C++ Productivity Tools
- VisualAge COBOL for Windows
- VisualAge PL/I for Windows

Both remote debuggers run on Windows NT 4.0, Windows 2000, and Windows XP.

Chapter 2. Debug Tool Utilities and Advanced Functions: introduction

Debug Tool Utilities and Advanced Functions enhances Debug Tool, and the combined strength of these products can help you debug and examine your programs.

Debug Tool provides a tool called Debug Tool Setup Utility (DTSU) to help you create and manage setup files which can help you run your programs. Debug Tool Utilities and Advanced Functions adds tools to help you do the following tasks:

- Prepare your high-level language programs for debugging by helping you convert, compile, and link.
- Prepare your assembler programs for debugging by helping you assemble, create debug information, and link.
- Conduct analysis on your test cases to determine how thoroughly your test cases test your programs (also called code coverage).
- Start and run your program in foreground or batch by storing and using setup information. Setup information can be the run-time parameters, libraries, and names of input and output data sets.
- For IMS Version 8, browse and edit the Language Environment run-time parameters table.
- Create a batch job for private IMS message region with customized load libraries and region attributes.
- Analyze load modules and program objects to identify the language translator used to generate the object for each CSECT.
- Convert old COBOL source code and copybooks to new versions of COBOL by using COBOL and CICS Command Level Conversion Aid (CCCA).

The combination of DTSU and these tools is called Debug Tool Utilities.

Debug Tool provides a rich set of commands to debug your programs. Debug Tool Utilities and Advanced Functions enhances this set of commands by adding the following commands:

- ALLOCATE
- CALL %CEBR
- CALL %CECI
- CALL %FA
- CALL %HOGAN
- DESCRIBE ALLOCATIONS
- FREE
- LOADDEBUGDATA or LDD
- PLAYBACK BACKWARD
- PLAYBACK DISABLE
- PLAYBACK ENABLE
- PLAYBACK FORWARD
- PLAYBACK START
- PLAYBACK STOP

- QUERY ASSEMBLER
- QUERY AUTOMONITOR
- QUERY PLAYBACK
- QUERY PLAYBACK LOCATION
- SET ASSEMBLER
- SET AUTOMONITOR
- SET PROGRAMMING LANGUAGE ASSEMBLER
- SET PROGRAMMING LANGUAGE OSVSCOBOL

Debug Tool Utilities: creating and managing setup files

Setup files can save you time when you are debugging a program that needs to be restarted multiple times. Setup files store information needed to run your program and start Debug Tool. You can create several setup files for each program; each setup file can store information about starting and running your program in different circumstances. To create and manage files, use Debug Tool Setup Utility (DTSU), which is part of Debug Tool. You do not need Debug Tool Utilities and Advanced Functions to use this tool.

Debug Tool Utilities: converting, compiling, and linking

Debug Tool Utilities helps you do the following tasks:

- Run the DB2 precompiler or the CICS translator.
If the program source is a sequential data set and the DB2 precompiler is selected, make sure the DBRMLIB data set field in EQAPPCnB panel, where $n=1,2,..5$, is a partitioned data set with a member name. For example, `DEBUG.TEST.DBRMLIB(PROG1)`.
- Set compiler options.
- Specify naming patterns for your data sets.
- Specify input data sets for copy processing.
- Convert, compile, and link-edit your programs in either TSO foreground or MVS batch.
- Prepare the following COBOL programs for debugging:
 - Programs written for OS/VS COBOL.
 - Programs previously compiled with the CMPR2 compiler option.

To prepare these programs, you convert the source to the newer COBOL standard and compile it with the newer compilers. After you debug your program, you can do one of the following:

 - Make changes to your OS/VS COBOL source and repeat the conversion and compilation every time you want to debug your program.
 - Make changes in the converted source and stop maintaining your OS/VS COBOL source.

Debug Tool Utilities: preparing assembler programs

By using High-Level Assembler (HLASM), Debug Tool Utilities can help you assemble and create debug information for your assembler programs. After your assembler program is assembled and the debug information is created, you can start Debug Tool and begin debugging your program.

Debug Tool Utilities: conducting code coverage

Determining code coverage can help you improve your test cases so they test your program more thoroughly. Debug Tool Utilities provides you with Debug Tool Coverage Utility, a tool to report which code statements have been run by your test cases. Using the report, you can enhance your test cases so they run code statements that were not run previously.

Debug Tool Utilities: preparing IMS run-time environment

You can create private IMS message regions that you can use to debug test applications and, therefore, not interfere with other regions. For IMS Version 8, you can modify the Language Environment run-time parameters table without relinking the applications.

Debug Tool Utilities: Load Module Analyzer

The Debug Tool Load Module Analyzer analyzes MVS load modules or program objects to determine the language translator (compiler or assembler) used to generate the object for each CSECT.

Starting Debug Tool Utilities

Debug Tool Utilities can be started in two ways. To determine which method to use on your system, contact your system administrator.

To start Debug Tool Utilities, do one the following:

- If an option was installed to access the Debug Tool Utilities primary options ISPF panel from an existing panel, then select that option by using instructions from the installer.
- If the Debug Tool data sets were installed into your normal logon procedure, enter the following command from the ISPF Command Shell panel (by default set as option 6):

```
EQASTART common_parameters
```

- If Debug Tool was not installed in your ISPF environment, enter this command from the ISPF Command Shell panel (by default set as option 6):

```
EX 'hlq.SEQAEXEC(EQASTART)' 'common_parameters'
```

The *common_parameters* are optional and specify any of the parameters described in Appendix E of *Coverage Utility User's Guide and Messages*. Multiple options are separated by blanks. Note that if you specify any of these *common_parameters*, your settings are remembered by EQASTART and become the default on subsequent starts of EQASTART when you do not specify parameters.

Chapter 3. Debugging a program in full-screen mode: introduction

Full-screen mode is the interface that Debug Tool provides to help you debug programs on a 3270 terminal. To debug a program in full-screen mode, you must compile or assemble your program with the proper options. “Compiling or assembling your program with the proper compiler options” gives an overview of the basic compiler or assembler tasks and directs you to other sections of this document that provide more detail.

This chapter gives an overview of basic debugging tasks and directs you to other sections of the document that provide more detail.

Compiling or assembling your program with the proper compiler options

Each programming language has a comprehensive set of compiler options. It's important to use the correct compiler options to debug your program.

Compiler options to use with C programs

The TEST compiler option provides suboptions to refine debugging capabilities. Use the defaults to gain maximum debugging capability.

Compiler options to use with C++ programs

The TEST compiler option provides suboptions to refine debugging capabilities. Use the defaults to gain maximum debugging capability.

Compiler options to use with COBOL programs

The TEST compiler option provides suboptions to refine debugging capabilities. Some suboptions are used only with a specific version of COBOL. This chapter assumes the use of suboptions available to all versions of COBOL.

Compiler options to use with OS/VS COBOL programs

When you compile your OS/VS COBOL program, the following options are required: NOTEST, SOURCE, DMAP, PMAP, VERB, XREF, NOLST, NOBATCH, NOSYMDMP, NOCOUNT.

Compiler options to use with PL/I programs

All PL/I programs must use the TEST compiler option and suboptions with the following stipulations:

- Programs compiled with the PL/I for MVS or OS PL/I compilers must also specify the SOURCE suboption.
- The syntax for the TEST compiler option of the Enterprise PL/I compilers is slightly different. Refer to the documentation that corresponds to the version of the compiler you are using for a description of the TEST compiler option.

Assembler options to use with assembler programs

When you assemble your program, you must specify the ADATA option. Specifying this option generates a SYSADATA file, which the EQALANGX postprocessor needs to create a debug file.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

- “Compiling a C program with the TEST compiler option” on page 37
- “Compiling a C program on an HFS file system” on page 39
- “Compiling your C program with the #pragma statement” on page 40
- “Compiling a C++ program with the TEST compiler option” on page 41
- “Compiling a C++ program on an HFS file system” on page 42
- “Compiling a COBOL program with the TEST compiler option” on page 25
- “Compiling a PL/I program with the TEST compiler option” on page 33
- “Compiling a Enterprise PL/I program on an HFS file system” on page 34
- “Compiling a PL/I for MVS & VM or OS PL/I program” on page 34
- Chapter 10, “Preparing an assembler program,” on page 45

Starting Debug Tool

You have a choice of several ways to start Debug Tool in full-screen mode in TSO:

- By using Debug Tool Utilities, which helps you compile or assemble your program and then start Debug Tool.
- When you start your Language Environment program, include the TEST run-time option as part of your command. For example:

```
CALL 'USERID1.MYLIB(MYPROGRM)' '/TEST'
```

Place the slash (/) before or after the TEST parameter, depending on the programming language you are debugging.

This is the simplest and most direct way to start Debug Tool. It also starts Debug Tool at the earliest point possible in your program.

- From within your Language Environment program, insert calls to `_ctest()`, `plitest`, or `ceetest` to start Debug Tool. This method is useful when you are familiar with your program and you know where you want debugging to begin.
- To start Debug Tool for a program that does not run in the Language Environment, you must start program EQANMDBG in MVS batch or TSO and pass the name of your program and any required Debug Tool run-time options as part of the PARM string.

When you start your program with the TEST run-time option, the Debug Tool screen appears:

```

COBOL      LOCATION: EMPLOOK initialization
Command ==>                               Scroll ==> PAGE
MONITOR --+---1---+---2---+---3---+---4---+---5---+---6 LINE: 0 OF 0
***** TOP OF MONITOR *****
***** BOTTOM OF MONITOR *****

SOURCE: EMPLOOK --1---+---2---+---3---+---4---+---5---+ LINE: 1 OF 349
1      *****
2      *
3      *
4      *****
5
6      *****
7      IDENTIFICATION DIVISION.
8      *****
9      PROGRAM-ID.      "EMPLOOK".
LOG 0---+---1---+---2---+---3---+---4---+---5---+---6- LINE: 1 OF 5
***** TOP OF LOG *****
0001 IBM Debug Tool Version 5 Release 1 Mod 0
0002 09/26/2004 10:02:39 AM
0003 5655-M18 and 5655-M19: (C) Copyright IBM Corp. 1992, 2004
PF 1:?      2:STEP      3:QUIT      4:LIST      5:FIND      6:AT/CLEAR
PF 7:UP      8:DOWN      9:GO      10:ZOOM      11:ZOOM LOG 12:RETRIEVE

```

The screen is divided into four sections:

Session panel header

The top two lines of the screen are header fields and a command line. The header fields describe the programming language and the location in the program. The command line is where you enter Debug Tool commands.

Monitor window

The second part of the screen is the Monitor window. It displays the results of the AUTOMONITOR and MONITOR commands.

Source window

The third part of the screen is the Source window. The Source window displays the source or listing file.

Log window

The fourth part of the screen is the Log window. It records your interactions with Debug Tool and the results of those interactions.

Now that you are familiar with the Debug Tool interface, you can begin debugging programs.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 16, “Starting Debug Tool by using the TEST run-time option,” on page 73

Chapter 17, “Starting Debug Tool from a program,” on page 79

“Starting Debug Tool with CEETEST” on page 79

“Starting Debug Tool with PLITEST” on page 85

“Starting Debug Tool with the __ctest() function” on page 86

Chapter 18, “Starting Debug Tool for batch or TSO programs,” on page 89

Chapter 19, “Starting Debug Tool under CICS,” on page 95

“Entering commands on the session panel” on page 114

“Navigating through Debug Tool session panel windows” on page 119

“Recording and replaying statements” on page 17

Related references

“Debug Tool session panel” on page 107

Stepping through a program

Stepping through a program means that you run a program one line at a time. After each line is run, you can observe changes in program flow and storage. These changes are displayed in the Monitor window, Source window, and Log window. Use the STEP command to step through a program.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Stepping through or running your program” on page 124

Running your program to a specific line

You can run from one point in a program to another point by using one of the following methods:

- Set a breakpoint and use the G0 command. This command runs your program from the point where it stopped to the breakpoint that you set. Any breakpoints that are encountered cause your program to stop. The RUN command is synonymous with the G0 command.
- Use the GOTO command. This command resumes your program at the point that you specify in the command. The code in between is skipped.
- Use the RUNTO command. This command runs your program to the point that you specify in the RUNTO command. The RUNTO command is helpful when you haven't set a breakpoint at the point you specify in the RUNTO command.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Setting a breakpoint

In Debug Tool, breakpoints can indicate a stopping point in your program and a stopping point in time. Breakpoints can also contain activities, such as instructions to run, calculations to perform, and changes to make.

A basic breakpoint indicates a stopping point in your program. For example, to stop on line 100 of your program, enter the following command on the command line:

```
AT 100
```

In the Log window, the message AT 100 ; appears. If line 100 is not a valid place to set a breakpoint, the Log window displays a message similar to Statement 100 is not valid. The breakpoint is also indicated in the Source window by a reversing of the colors in the prefix area.

Breakpoints do more than just indicate a place to stop. Breakpoints can also contain instructions. For example, the following breakpoint instructs Debug Tool to display the contents of the variable *myvar* when Debug Tool reaches line 100:

```
AT 100 LIST myvar;
```

A breakpoint can contain instructions that alter the flow of the program. For example, the following breakpoint instructs Debug Tool to go to label `newPlace` when it reaches line 100:

```
AT 100 GOTO newPlace ;
```

A breakpoint can contain complex instructions. In the following example, when Debug Tool reaches line 100, it alters the contents of the variable `myvar` if the value of the variable `mybool` is true:

```
AT 100 if (mybool == TRUE) myvar = 10 ;
```

The syntax of the complex instruction depends on the program language that you are debugging. The previous example assumes that you are debugging a C program. If you are debugging a COBOL program, the same example is written as follows:

```
AT 100 if mybool = TRUE THEN myvar = 10 ; END-IF ;
```

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Displaying the value of a variable

After you are familiar with setting breakpoints and running through your program, you can begin displaying the value of a variable. The value of a variable can be displayed in one of the following ways:

- One-time display (in the Log window) is useful for quickly checking the value of a variable.
- Continuous display (in the Monitor window) is useful for observing the value of a variable over time.
- A combination of one-time and continuous display, where the value of variables coded in the current line are displayed, is useful for observing the value of variables when the variables are used.

For one-time display, enter the following command on the command line, where `x` is the name of the variable:

```
LIST (x)
```

The Log window shows a message in the following format:

```
LIST ( x ) ;  
x = 10
```

For continuous display, enter the following command on the command line, where `x` is the name of the variable:

```
MONITOR LIST ( x )
```

In the Monitor window, a line appears with the name of the variable and the current value of the variable next to it. If the value of the variable is undefined, the variable is not initialized, or the variable does not exist, a message appears underneath the variable name declaring the variable unusable.

For a combination of one-time and continuous display, enter the following command on the command line:

```
SET AUTOMONITOR ON ;
```

After a line of code is run, the Monitor window displays the name and value of each variable on the line of code. You must purchase and install Debug Tool Utilities and Advanced Functions, Version 5 Release 1 (5655-M19) before using the SET AUTOMONITOR command. The SET AUTOMONITOR command can be used only with specific programming languages, as described in *Debug Tool for z/OS Reference and Messages*.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Displaying values of C and C++ variables or expressions” on page 238

“Displaying values of COBOL variables” on page 213

“Displaying and monitoring the value of a variable” on page 127

Related references

“Monitor window” on page 111

Debug Tool for z/OS Reference and Messages

Changing the value of a variable

After you see the value of a variable, you might want to change the value. If, for example, the assigned value isn't what you expect, you can change it to the desired value. You can then continue to study the flow of your program, postponing the analysis of why the variable wasn't set correctly.

Changing the value of a variable depends on the programming language that you are debugging. In Debug Tool, the rules and methods for the assignment of values to variables are the same as programming language rules and methods. For example, to assign a value to a C variable, use the C assignment rules and methods:

```
var = 1 ;
```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Assigning values to C and C++ variables” on page 239

“Assigning values to COBOL variables” on page 211

Skipping a breakpoint

Use the DISABLE command to temporarily disable a breakpoint. Use the ENABLE command to re-enable the breakpoint.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Clearing a breakpoint

When you no longer require a breakpoint, you can clear it. Clearing it removes any of the instructions associated with that breakpoint. For example, to clear a breakpoint on line 100 of your program, enter the following command on the command line:

```
CLEAR AT 100
```

The Log window displays a line that says CLEAR AT 100 ; and the prefix area reverts to its original colors. These changes indicate that the breakpoint at line 100 is gone.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Recording and replaying statements

The commands described in this section are available only if you purchase and install IBM Debug Tool Utilities and Advanced Functions, Version 5 Release 1 (5655-M19).

You can record and subsequently replay statements that you run. When you replay statements, you can replay them in a forward direction or a backward direction. Table 4 describes the sequence in which statements are replayed when you replay them in a forward direction or a backward direction.

Table 4. The sequence in which statements are replayed.

PLAYBACK FORWARD sequence	PLAYBACK BACKWARD sequence	COBOL Statements
1	9	DISPLAY "CALC Begins."
2	8	MOVE 1 TO BUFFER-PTR.
3	7	PERFORM ACCEPT-INPUT 2 TIMES.
8	2	DISPLAY "CALC Ends."
9	1	GOBACK.
		ACCEPT-INPUT.
4, 6	4, 6	ACCEPT INPUT-RECORD FROM A-INPUT-FILE
5, 7	3, 5	MOVE RECORD-HEADER TO REPROR-HEADER.

To begin recording, enter the following command:

PLAYBACK ENABLE

Statements that you run after you enter the PLAYBACK ENABLE command are recorded.

To replay the statements that you record:

1. Enter the PLAYBACK START command.
2. To move backward one statement, enter the STEP command.
3. Repeat step 2 as many times as you can to replay another statement.
4. To move forward (from the current statement to the next statement), enter the PLAYBACK FORWARD command.
5. Enter the STEP command to replay another statement.
6. Repeat step 5 as many times as you want to replay another statement.
7. To move backward, enter the PLAYBACK BACKWARD command.

PLAYBACK BACKWARD and PLAYBACK FORWARD change the direction commands like STEP move in.

When you have finished replaying statements, enter the PLAYBACK STOP command. Debug Tool returns you to the point at which you entered the PLAYBACK START command. You can resume normal debugging. Debug Tool continues to record your statements. To replay a new set of statements, begin at step 1 on page 17.

When you finish recording and replaying statements, enter the following command:

PLAYBACK DISABLE

Debug Tool no longer records any statements and discards information that you recorded. The PLAYBACK START, PLAYBACK FORWARD, PLAYBACK BACKWARD, and PLAYBACK STOP commands are no longer available.

Stopping Debug Tool

To stop your debug session, do the following steps:

1. Enter the QUIT command.
2. In response to the message to confirm your request to stop your debug session, press "Y" and then press Enter.

Your Debug Tool screen closes.

Refer to *Debug Tool for z/OS Reference and Messages* for more information on the QQUIT, QUIT ABEND and QUIT DEBUG commands which can stop your debug session.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Part 2. Preparing your program for debugging

Chapter 4. Planning your debug session and collecting resources

Before you begin debugging, you should plan how you want to conduct your debug session and then collect the resources you need to implement your plan. To help you create your plan, consider following questions:

- Do you want to compile your program with hooks?
- Do you want to reference variables during your debug session?
- Do you want full debug capability or smaller application size and higher performance?
- When do you want to start Debug Tool and when do you want it to gain control?
- Do you want to use Debug Tool in full-screen mode, in batch mode, or in remote debug mode?

The sections in this chapter provide answers to these questions which can help you determine how you want to conduct your debug session.

Refer to the following sections for more information related to the material discussed in this section.

Related concepts

“Debug Tool interfaces” on page 4

Chapter 2, “Debug Tool Utilities and Advanced Functions: introduction,” on page 7

Related tasks

Chapter 5, “Preparing a COBOL program,” on page 25

Chapter 7, “Preparing a PL/I program,” on page 33

Chapter 8, “Preparing a C program,” on page 37

Chapter 9, “Preparing a C++ program,” on page 41

Chapter 10, “Preparing an assembler program,” on page 45

Chapter 11, “Preparing a DB2 program,” on page 49

Chapter 12, “Preparing a DB2 stored procedures program,” on page 53

Chapter 13, “Preparing a CICS program,” on page 55

Chapter 14, “Preparing an IMS program,” on page 63

Chapter 42, “Debugging programs in a production environment,” on page 289

Do you want your program to have hooks?

Hooks enable you to set breakpoints. Hooks are instructions that can be inserted into a program by a compiler at compile time. Hooks can be placed at the entrances and exits of blocks, at statement boundaries, and at points in the program where program flow might change between statement boundaries (called path points). If you compile a program with the TEST compiler option and specify any suboption except NONE, the compiler inserts hooks into your program.

Assembler, disassembly, and OS/VS COBOL programs are always created without hooks.

If you use one of the following compilers, you can compile your programs without hooks by using the TEST(NONE) compiler option:

- Enterprise COBOL for z/OS and OS/390, Version 3

- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1, with APAR PQ40298

If you use the Enterprise PL/I for z/OS, Version 3 Release 4, compiler, you can compile your programs without hooks by using the TEST(NOHOOK) compiler option.

To debug these programs or to debug assembler, disassembled, or OS/VS COBOL programs, you must use the Dynamic Debug facility. The Dynamic Debug facility enables you to set breakpoints in a program that does not have hooks. The hooks are inserted at run time whenever you set a breakpoint or enter the step command.

When you compile with one of the following compilers and have the compiler insert hooks, you can enhance the program's performance while you debug it by using the Dynamic Debug facility:

- any COBOL compiler supported by Debug Tool
- any PL/I compiler supported by Debug Tool
- any C/C++ compiler supported by Debug Tool

Some path breakpoints might be unavailable when you use the Dynamic Debug facility.

Do you want to reference variables during your debug session?

If yes, you need to instruct the compiler or assembler to create a symbol table. The symbol table contains descriptions of variables, their attributes, and their location in storage. Debug Tool uses these descriptions when it references variables. The symbol tables can be stored in the object file of the program or in a separate debug file. You can save symbol tables in a separate debug file if you compile or assemble your programs with one of the following compilers or assemblers:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298
- OS/VS COBOL Version 1, Release 2.4
- High Level Assembler for MVS & VM & VSE, Release 4

Saving symbol tables in a separate debug file can reduce the size of the load module for your program.

Do you want full debug capability or smaller application size and higher performance?

Removing hooks, statement tables, or symbol tables can increase the performance of your application and decrease its size. However, debug capabilities are diminished.

To decrease the size of your application, increase performance, and retain most debug capabilities, you can compile COBOL programs with the TEST(NONE,SYM,SEPARATE) compiler option, which is available with one of the following compilers:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2

- COBOL for OS/390 & VM, Version 2 Release 1, with APAR PQ40298

The Dynamic Debug facility must be activated. To determine if the Dynamic Debug facility is active, enter the QUERY DYNDEBUG command after your debug session has started or contact your system administrator. If your programs are running on OS/390, Version 2 Release 10, or z/OS, Version 1 Release 1, you need to install Language Environment APAR PQ46488.

You can improve the performance of Debug Tool while debugging programs compiled with any of the following compilers by using the Dynamic Debug facility:

- any COBOL compiler supported by Debug Tool
- any PL/I compiler supported by Debug Tool
- any C/C++ compiler supported by Debug Tool

When do you want to start Debug Tool and when do you want it to gain control?

You have a choice of ways to start Debug Tool, as well as ways to let it gain control of your program.

If you are debugging TSO or batch programs, you can start Debug Tool in one of the following ways:

- You can use Debug Tool Setup Utility, which you can access by using Debug Tool Utilities to start your program. Debug Tool Setup Utility can help you prepare your programs and start Debug Tool.
- You can use the TEST run-time option to start your Language Environment program. This option gives you the choice of starting Debug Tool at any of these times:
 - Before you run your program
 - When a high-level language (HLL) condition occurs while your program is running
 - When an attention interrupt occurs (except for batch programs)

Also, Language Environment, as well as certain HLLs, provides a run-time service that you can call while your program is executing, at the location of your choice.

- You can start Debug Tool by using EQANMDBG to start your MVS batch or TSO program that does not start in Language Environment including OS/VS COBOL programs.

If you are debugging DB2, IMS, or CICS programs, you can start Debug Tool in the way described in the following sections:

- “Debugging DB2 programs in batch mode” on page 277
- “Debugging DB2 programs in full-screen mode” on page 277
- “Debugging IMS programs in interactive mode” on page 281
- “Debugging IMS programs in batch mode” on page 282
- Chapter 19, “Starting Debug Tool under CICS,” on page 95

After Debug Tool starts, it gains control of your program and suspends execution so that you can take actions such as checking the value of a variable or examining the contents of storage.

Do you want to use Debug Tool in full-screen mode, in batch mode, or in remote debug mode?

Decide which interface you want to use when debugging your program. The interface that you choose affects how you start your program, how you start Debug Tool, and how you interact with Debug Tool.

Collecting your resources

After you determine how you want to conduct your debug session, collect the resources you need to prepare and debug your programs. The minimum requirement is the source file to compile or assemble your program and access to the compiler or assembler to prepare your program. The following list describes additional resources you might need, depending on the type of program you are debugging:

To debug a program that is optimized

If you are debugging a COBOL program that is optimized, you need to save the debug information in a separate debug file and you need to use the Dynamic Debug facility. You also need to use the compilers that support the SEPARATE suboption of the TEST compiler option.

To debug a program without hooks

If you are debugging a program without hooks, you need the Dynamic Debug facility to debug your program.

To debug an assembler or OS/VS COBOL program

If you are debugging an assembler or OS/VS COBOL program, you need to create the EQALANGX file.

To debug a program without debug information

If you are debugging a program without debug information, you need to use the disassembly view and have a hardcopy of the listing available.

Chapter 5. Preparing a COBOL program

Before you debug a program, ensure that the program complies with the requirements described in this book:

- All the data sets required to debug your program comply with the guidelines described in this book.
- All the libraries that your program needs are available.
- Your program is compiled with the appropriate compiler options.

When a program is under development, compile the program with the TEST(ALL) compiler option to get all of Debug Tool's capabilities. If you use one of the following compilers, you can compile COBOL programs with the TEST(NONE,SYM,SEPARATE) compiler option and retain most of Debug Tool's capabilities:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298

Appendix C, "Examples: Preparing programs and modifying setup files with Debug Tool Utilities," on page 327 describes how to prepare a sample COBOL program and start Debug Tool by using Debug Tool Utilities.

Depending on the compiler and compiler options you select, you need to save the source, listing, or separate debug file, which Debug Tool needs to display your source. Refer to Appendix A, "Data sets used by Debug Tool," on page 321 for a description of which file you need to save.

Compiling a COBOL program with the TEST compiler option

The suboptions you specify when you compile your COBOL program with the TEST compiler option affect the size and performance of your program and the debugging capabilities available. Before debugging your COBOL program with Debug Tool, you must compile it with the COBOL TEST compiler option. Depending on the suboptions you specify, the compiler does the following:

- Creates the symbol tables.
- Creates debugging information.
- Inserts hooks at selected points in your program.

Debug Tool uses the symbol tables to obtain information about program variables. Programs compiled with one of the following compilers and with the SEPARATE suboption store debugging information and symbol tables in a separate file.

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298

The file, called a separate debug file, must be a non-temporary file and must also be available during the debug session. If you move or rename the separate debug file, specify the new location by using one of the following methods:

- Entering the SET SOURCE command with the name of the new location
- Entering the SET DEFAULT LISTINGS command with the name of the new location

- Specifying the EQADEBUG DD statement with the name of the new location
- Coding the EQAUEDAT user exit with the new location

Debug Tool uses hooks to gain control of your program at selected points during its execution. The hooks do not modify your source. The hooks are inserted into your program during one of the following times:

- At compile time, when you specify the TEST compiler option with any suboption except NONE. Hooks can be inserted at the entrances and exits of blocks, at statement boundaries, and at points in the program where program flow might change between statement boundaries (called path points), such as before and after a CALL statement.

- At run time, if the Dynamic Debug facility is activated (which is the default). The hooks are inserted when you set a breakpoint or enter the STEP command.

If your program has compiled-in hooks and you choose to use the Dynamic Debug facility to take advantage of improved performance, the hooks that are inserted at run time are used instead of the compiled-in hooks.

To debug programs that do not have compiled-in hooks, use the Dynamic Debug facility while you debug and compile your programs with the TEST(NONE) compiler option with one of the following compilers:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298

If programs compiled with the TEST(NONE) compiler option are running on OS/390, Version 2 Release 10, or z/OS, Version 1 Release 1, you need to install Language Environment APAR PQ46488.

If the Dynamic Debug facility is used to place hooks in programs that reside in read-only storage, the Authorized Debug facility must be installed and you must be authorized to use it. Contact your system administrator to get authorized.

When you use the COBOL TEST compiler option:

- If you specify NUMBER with TEST, make sure the sequence fields in your source code all contain numeric characters.
- Usually, when you specify TEST in combination with any other suboptions (except NONE), the compiler options NOOPTIMIZE and OBJECT automatically go into effect, preventing you from debugging optimized programs. However, if you specify TEST(NONE,SYM) and compile with one of the following compilers, you can specify OPT, allowing you to debug optimized programs:
 - Enterprise COBOL for z/OS and OS/390, Version 3 Release 2
 - Enterprise COBOL for z/OS and OS/390, Version 3 Release 1 with APAR PQ63235
 - COBOL for OS/390 & VM, Version 2 with APAR PQ63234
- The TEST compiler option and the DEBUG run-time option are mutually exclusive, with DEBUG taking precedence. If you specify both the WITH DEBUGGING MODE clause in your SOURCE-COMPUTER paragraph and the USE FOR DEBUGGING statement in your code, TEST is deactivated. The TEST compiler option appears in the list of options, but a diagnostic message is issued telling you that because of the conflict, TEST is not in effect.
- If you want to use the DATA suboption of the PLAYBACK ENABLE command, you must specify the SYM suboption of the TEST compiler option when you compile your program.

- For VS COBOL II programs, in addition to the TEST compiler option, you must specify:
 - the SOURCE compiler option. This option is required to generate a listing file.
 - the RESIDENT compiler option. This option is required by Language Environment to ensure that the necessary Debug Tool routines are loaded dynamically at run time.

In addition, you must link your program with the Language Environment SCEELKED library and not the VS COBOL II COB2LIB library.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Converting an OS/VS COBOL program to 1985 COBOL Standard

Programs compiled with the OS/VS COBOL compiler can be debugged by converting them to the 1985 COBOL Standard level and compiling them with the Enterprise COBOL for z/OS and OS/390 or COBOL for OS/390 & VM compiler. This conversion and compilation can be done with the Convert and Compile option provided in Debug Tool Utilities. To use Debug Tool Utilities, you must purchase and install Debug Tool Utilities and Advanced Functions, Version 5 Release 1 (5655-M19).

The Convert and Compile option enables you to do the following:

1. Convert your OS/VS COBOL source by using COBOL and CICS Command Level Conversion Aid (CCCA).
2. Compile new source with either the Enterprise COBOL for z/OS and OS/390 or COBOL for OS/390 & VM.
3. Debug the object module by using Debug Tool.

After you convert and debug your program, you can do one of the following:

- Continue to use the OS/VS COBOL compiler. Every time you want to debug your program, you need to use the Convert and Compile option.
- Use the new source that was produced by the Convert and Compile option. You can compile it and debug it without using the Convert and Compile option.

The Convert and Compile option can use any level of COBOL source program as input, including VS COBOL II, COBOL for MVS & VM, and COBOL for OS/390 & VM programs that were previously compiled with the CMPR2 compiler option.

Chapter 6. Preparing an OS/VS COBOL program

This chapter describes how to prepare an OS/VS COBOL program that you can debug with Debug Tool. You must have Debug Tool Utilities and Advanced Functions installed on your system to prepare and debug an OS/VS COBOL programs.

To prepare an OS/VS COBOL program, you must do the following steps:

1. Compile your program with the IBM OS/VS COBOL compiler using the proper options.
2. Create the EQALANGX file.
3. Link-edit your program.

As you read through the information in this document, remember that OS/VS COBOL programs are non-Language Environment programs, even though you might have used Language Environment libraries to link and run your program. Please read the information regarding non-Language Environment programs for instructions on how to start Debug Tool and debug OS/VS COBOL programs, unless OS/VS COBOL-specific information is provided.

Compiling your OS/VS COBOL program

You must compile your OS/VS COBOL program with the IBM OS/VS COBOL compiler and use the following options:

- NOTEST
- SOURCE
- DMAP
- PMAP
- VERB
- XREF
- NOLST
- NOBATCH
- NOSYMDMP
- NOCOUNT

Creating the EQALANGX file

To create the EQALANGX file, you use the EQALANGX program. The EQALANGX program shipped as a component of Debug Tool is functionally equivalent to the IDILANGX program shipped as a component of IBM Fault Analyzer. If you have IBM Fault Analyzer installed, you can use the IDILANGX program to create the EQALANGX file, as long as the version of the IDILANGX program is the same as or newer than the EQALANGX program shipped with Debug Tool. To identify the version of the program, do the following steps:

1. Create the EQALANGX file as described in the IBM Fault Analyzer documentation.
2. Look at the first record of the generated EQALANGX file and make a note of the version.
3. Create the EQALANGX file as described in this section.

4. Look at the first record of the generated EQALANGX file.

If you choose to use IDILANGX to create the EQALANGX file, you can skip these instructions. See the IBM Fault Analyzer documentation for instructions on creating the EQALANGX file.

To create the EQALANGX file, do the following steps:

1. Create JCL similar to the following:

```
//XTRACT EXEC PGM=EQALANGX,REGION=32M,  
// PARM='(COBOL ERROR LOUD'  
//STEPLIB DD DISP=SHR,DSN=hlq.SEQAMOD  
//LISTING DD DISP=SHR,DSN=yourid.osvscompiler.listing  
//IDILANGX DD DISP=OLD,DSN=yourid.EQALANGX
```

The following list describes the variables used in this example and the parameters you can use with the EQALANGX program:

PARM=

(COBOL

The (COBOL parameter indicates that an OS/VS COBOL module is being processed.

ERROR

The ERROR parameter is suggested, but optional. If you specify it, additional information is displayed when an error is detected.

LOUD

The LOUD parameter is suggested, but optional. If you specify it, additional informational and statistical messages are displayed.

64K CREF

The 64K and CREF parameters are optional. Previously, these options were required.

The messages displayed by specifying the ERROR and LOUD parameters are Write To Operator or Write To Programmer (WTO or WTP) messages. See the *IBM Fault Analyzer for z/OS User's Guide and Reference* for detailed information about the messages and return codes displayed by the IDILANGX program. The EQALANGX program uses the same messages and return codes.

hlq.**SEQAMOD**

The name of the data set containing the Debug Tool load modules. If the Debug Tool load modules are in a system linklib data set, you can omit the following line:

```
//STEPLIB DD DISP=SHR,DSN=hlq.SEQAMOD
```

yourid.osvscompiler.listing

The name of the listing data set generated by the IBM OS/VS COBOL compiler. If this is a partitioned data set, the member name must be specified. For information about the characteristics of this data set, see *IBM OS/VS COBOL Compiler Programmer's Guide*.

yourid.**EQALANGX**

The name of the data set where the EQALANGX debug file is to be placed. This data set must have variable block record format (RECFM=VB) and a logical record length of 1562 (LRECL=1562).

Debug Tool searches for the EQALANGX debug file in a partitioned data set with the name *yourid*.EQALANGX and a member name that matches

the name of the OS/VS COBOL program. If you want the member name of the EQALANGX debug file to match the name of the OS/VS COBOL program, you do not need to specify a member name on the DD statement.

2. Submit the JCL and verify that the EQALANGX file is created in the location you specified on the IDILANGX DD statement.

Link-editing your program

You can link-edit your program by using your normal link-edit procedures.

After you link-edit your program, you can run your program and start Debug Tool.

Chapter 7. Preparing a PL/I program

Before you debug a program, ensure that the program complies with the requirements described in this book:

- All the data sets required to debug your program comply with the guidelines described in this book.
- All the libraries that your program needs are available.
- Your program is compiled with the appropriate compiler options.

When a program is under development, you should compile the program with the TEST(ALL) compiler option to get all of Debug Tool's capabilities.

Appendix C, "Examples: Preparing programs and modifying setup files with Debug Tool Utilities," on page 327 describes how to prepare a sample PL/I program and start Debug Tool by using Debug Tool Utilities.

Depending on the compiler and compiler options you select, you need to save the source, listing, or separate debug file, which Debug Tool needs to display your source. Refer to Appendix A, "Data sets used by Debug Tool," on page 321 for a description of which file you need to save.

Compiling a PL/I program with the TEST compiler option

The PL/I compiler provides the TEST compiler option and its suboptions to control the placement of hooks and symbol tables. The suboptions BLOCK, STMT, PATH, ALL, and NONE regulate the points at which the compiler inserts hooks. Debug Tool uses these hooks to gain control of the program at select points while it is running. The suboptions SYM or NOSYM control the insertion of symbol tables into the program's object file. Debug Tool uses the symbol tables to obtain information about program variables. In Enterprise PL/I for z/OS, Version 3 Release 4, a new pair of suboptions was added: HOOK and NOHOOK. These suboptions control the insertion of hook-related information into the program's object file.

If all of the following tasks are completed, Debug Tool uses the hooks inserted by the Dynamic Debug facility instead of the hooks inserted by the compiler:

- The Dynamic Debug facility is installed on your system.
- You have not deactivated the Dynamic Debug facility by entering the SET DYNDEBUG OFF command.

Using the hooks inserted by the Dynamic Debug facility provides better performance when you are debugging your program. However, some path breakpoints become unavailable. If you need to use those breakpoints, deactivate the Dynamic Debug facility by entering the SET DYNDEBUG OFF command.

If you compile your program with Enterprise PL/I for z/OS, Version 3 Release 4, you can use the NOHOOK suboption of the TEST compiler option to prevent compiler generated hooks from being inserted into the program. To debug the program, you must activate the Dynamic Debug facility.

If you are debugging a C/C++ or Enterprise PL/I program, do not associate SYSIN with an in-stream data set (for example //SYSIN DD *).

If the Dynamic Debug facility is used to place hooks in programs that reside in read-only storage, the Authorized Debug facility must be installed and you must be authorized to use it. Contact your system administrator to get authorized.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Compiling a Enterprise PL/I program on an HFS file system

If you are compiling and launching Enterprise PL/I programs on an HFS file system, you must do one of the following:

- Compile and launch the programs from the same location, or
- specify the full path name when you compile the programs.

By default, the Enterprise PL/I compiler stores the relative path and file names in the object file. When you start a debug session, if the source is not in the same location as where the program is launched, Debug Tool does not locate the source. To avoid this problem, specify the full path name for the source when you compile the program. For example, if you execute the following series of commands, Debug Tool does not find the source because it is located in another directory (/u/myid/mypgm):

1. Change to the directory where your program resides and compile the program.

```
cd /u/myid/mypgm  
pli -g "//TEST.LOAD(HELLO)" hello.pli
```
2. Exit UNIX System Services and return to the TSO READY prompt.
3. Launch the program with the TEST run-time option.

```
call TEST.LOAD(HELLO) 'test/'
```

Debug Tool does find the source if you change the compile command to:

```
pli -g "//TEST.LOAD(HELLO)" /u/myid/mypgm/hello.pli
```

The same restriction applies to programs that you compile to run in a CICS environment.

Compiling a PL/I for MVS & VM or OS PL/I program

For OS PL/I programs, you must specify the SOURCE compiler option in addition to the TEST compiler option. The SOURCE compiler option is required to generate a listing file. In addition, you must link your program with the Language Environment SCEELKED library; do not use the OS PL/I PLIBASE or SIBMBASE library.

To be able to view your listing while debugging in full-screen mode, PL/I for MVS & VM and OS PL/I programs must be compiled using the SOURCE compiler option. You must also direct the listing to a non-temporary file that is available during the debug session. During a debug session, Debug Tool displays the first file it finds named `userid.pgmname.list` in the Source window. If Debug Tool cannot find the listing at this location, use one of the following methods to associate your source listing with the program you are debugging:

- Entering the SET SOURCE command with the name of the location or file.
- Entering the SET DEFAULT LISTINGS command with the name of the location or file.

- Specifying the EQADEBUG DD statement with the name of the location or file.
- Coding the EQAUEDAT user exit with the new location.

Chapter 8. Preparing a C program

Before you debug a program, ensure that the program complies with the requirements described in this book:

- All the data sets required to debug your program comply with the guidelines described in this book. The source must be in a single file and not a concatenation of files.
- All the libraries that your program needs are available.
- Your program is compiled with the appropriate compiler options.

When a program is under development, you can get the full capability of Debug Tool by compiling your program with the TEST(ALL) compiler option.

Appendix C, “Examples: Preparing programs and modifying setup files with Debug Tool Utilities,” on page 327 describes how to prepare a sample C program and start Debug Tool by using Debug Tool Utilities.

Depending on the compiler and compiler options you select, you need to save the source, listing, or separate debug file, which Debug Tool needs to display your source. Refer to Appendix A, “Data sets used by Debug Tool,” on page 321 for a description of which file you need to save.

Compiling a C program with the TEST compiler option

Before you test your C program with Debug Tool, you must compile it with the C TEST compiler option:

- The suboptions BLOCK, LINE, and PATH regulate the points where the compiler inserts program hooks. When you set breakpoints, they are associated with the hooks that are used to instruct Debug Tool where to gain control of your program.
- The suboption SYM regulates the inclusion of symbol tables into the object output of the compiler. Debug Tool uses the symbol tables to obtain information about the variables in the program.

When you use the C TEST compiler option, be aware that:

- The C TEST compiler option generates hooks at entry and exit points for functions.
- The C TEST compiler option implicitly specifies the GONUMBER compiler option, which causes the compiler to generate line number tables that correspond to the input source file. You can explicitly remove this option by specifying NOGONUMBER. When the TEST and NOGONUMBER options are specified together, Debug Tool does not display the current execution line as you step through your code.
- Programs that are compiled with both the TEST compiler option and either the OPT(1) or OPT(2) compiler option do not have hooks at line, block, and path points, or generate a symbol table, regardless of the TEST suboptions specified. Only hooks for function entry and exit points are generated for optimized programs.
- You can specify any number of TEST suboptions, including conflicting suboptions (for example, both PATH and NOPATH). The last suboptions that are specified take effect. For example, if you specify TEST(BLOCK, NOBLOCK, BLOCK, NOLINE, LINE), what takes effect is TEST(BLOCK, LINE) because BLOCK and LINE are specified last.

- No duplicate hooks are generated even if two similar TEST suboptions are specified. For example, if you specify TEST(BLOCK, PATH), the BLOCK suboption causes the generation of hooks at entry and exit points. The PATH suboption also causes the generation of hooks at entry and exit points. However, only one hook is generated at each entry and exit point.

If you are debugging a C/C++ or Enterprise PL/I program, do not associate SYSIN with an in-stream data set (for example //SYSIN DD *).

You can specify any combination of the C TEST suboptions in any order. The default suboptions are BLOCK, LINE, PATH, and SYM.

If all of the following tasks are completed, Debug Tool uses the hooks inserted by the Dynamic Debug facility instead of the hooks inserted by the compiler:

- The Dynamic Debug facility is installed on your system.
- You have not deactivated the Dynamic Debug facility by entering the SET DYNDEBUG OFF command.

Using the hooks inserted by the Dynamic Debug facility provides better performance when you are debugging your program. However, some path breakpoints become unavailable. If you need to use those breakpoints, deactivate the Dynamic Debug facility by entering the SET DYNDEBUG OFF command.

If the Dynamic Debug facility is used to place hooks in programs that reside in read-only storage, the Authorized Debug facility must be installed and you must be authorized to use it. Contact your system administrator to get authorized.

If you build your application using the c89 or c++, do the following steps:

1. Compile your source code as usual, but specify the -g option to generate debugging information. The -g option is equivalent to the TEST compiler option under TSO or MVS batch. For example, to compile the C source file fred.c from the u/mike/app directory, specify:

```
cd /u/mike/app
c89 -g -o "//PROJ.LOAD(FRED)" fred.c
```

Note: The double quotes in the command line above are required.

2. Set up your TSO environment, as described above.
3. Debug the program under TSO by entering the following:

```
FRED TEST ENVAR('PWD=/u/mike/app') / asis
```

Note: The single quotes in the command line above are required.

ENVAR('PWD=/u/mike/app') sets the environment variable PWD to the path from where the source files were compiled. Debug Tool uses this information to determine from where it should read the source files.

If you are debugging your application in the UNIX System Services Shell, you must debug in remote debug mode or in full-screen mode through a VTAM terminal. The workstation component of remote debuggers is available through several products, including C and C++ Productivity Tools for OS/390 and VisualAge COBOL.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Compiling a C program on an HFS file system

If you are compiling and launching programs on an HFS file system, you must do one of the following:

- Compile and launch the programs from the same location.
- Specify the full path name when you compile the programs.

By default, the C compiler stores the relative path and file names of the source files in the object file. When you start a debug session, if the source is not in the same location as where the program is launched, Debug Tool does not find the source. To avoid this problem, specify the full path name of the source when you compile the program. For example, if you execute the following series of commands, Debug Tool does not find the source because it is located in another directory

(/u/myid/mypgm):

1. Change to the directory where your program resides and compile the program.

```
cd /u/myid/mypgm
c89 -g -o "//TEST.LOAD(HELLO)" hello.c
```

2. Exit UNIX System Services and return to the TSO READY prompt.

3. Launch the program with the TEST run-time option.

```
call TEST.LOAD(HELLO) 'test/'
```

Debug Tool finds the source if you change the compile command to:

```
c89 -g -o "//TEST.LOAD(HELLO)" /u/myid/mypgm/hello.c
```

The same restriction applies to programs that you compile to run in a CICS environment.

Rules for the placement of hooks in functions and nested blocks

The following rules apply to the placement of hooks for getting in and out of functions and nested blocks:

- The hook for function entry is placed before any initialization or statements for the function.
- The hook for function exit is placed just before actual function return.
- The hook for nested block entry is placed before any statements or initialization for the block.
- The hook for nested block exit is placed after all statements for the block.

Rules for placement of hooks in statements and path points

The following rules apply to the placement of hooks for statements and path points:

- Label hooks are placed before the code and all other statement or path point hooks for the statement.
- The statement hook is placed before the code and path point hook for the statement.
- A path point hook for a statement is placed before the code for the statement.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Compiling your C program with the #pragma statement” on page 40

Compiling your C program with the #pragma statement

The TEST/NOTEST compiler option can be specified either when you compile your program or directly in your program, using a #pragma.

This #pragma must appear before any executable code in your program.

The following example generates symbol table information, symbol information for nested blocks, and hooks at line numbers:

```
#pragma options (test(SYM,BLOCK,LINE))
```

This is equivalent to TEST(SYM,BLOCK,LINE,PATH).

You can also use a #pragma to specify run-time options.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 8, "Preparing a C program," on page 37

Chapter 9, "Preparing a C++ program," on page 41

C/C++ Language Reference

Chapter 9. Preparing a C++ program

Before you debug a program, ensure that the program complies with the requirements described in this book:

- All the data sets required to debug your program comply with the guidelines described in this book. This includes that the source must be in a single file and not a concatenation of files.
- All the libraries that your program needs are available.
- Your program is compiled with the appropriate compiler options.

When a program is under development, you should compile the program with the TEST(ALL) compiler option to get all of Debug Tool's capabilities.

Appendix C, "Examples: Preparing programs and modifying setup files with Debug Tool Utilities," on page 327 describes how to prepare a sample C++ program and start Debug Tool by using Debug Tool Utilities.

Depending on the compiler and compiler options you select, you need to save the source, listing, or separate debug file, which Debug Tool needs to display your source. Refer to Appendix A, "Data sets used by Debug Tool," on page 321 for a description of which file you need to save.

Compiling a C++ program with the TEST compiler option

Before testing your C++ program with Debug Tool, you must compile it with the C++ TEST compiler option. This causes the compiler to generate information about your program that Debug Tool needs to help you debug your program.

If you are debugging a C/C++ or Enterprise PL/I program, do not associate SYSIN with an in-stream data set (for example //SYSIN DD *).

If all of the following tasks are completed, Debug Tool uses the hooks inserted by the Dynamic Debug facility instead of the hooks inserted by the compiler:

- The Dynamic Debug facility is installed on your system.
- You have not deactivated the Dynamic Debug facility by entering the SET DYNDEBUG OFF command.

Using the hooks inserted by the Dynamic Debug facility provides better performance when you are debugging your program. However, some path breakpoints become unavailable. If you need to use those breakpoints, deactivate the Dynamic Debug facility by entering the SET DYNDEBUG OFF command.

If the Dynamic Debug facility is used to place hooks in programs that reside in read-only storage, the Authorized Debug facility must be installed and you must be authorized to use it. Contact your system administrator to get authorized.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Compiling a C++ program on an HFS file system

If you are compiling and launching programs on an HFS file system, you must do one of the following:

- Compile and launch the programs from the same location, or
- specify the full path name when you compile the programs.

By default, the C++ compiler stores the relative path and file names of the source files in the object file. When you start a debug session, if the source is not in the same location as where the program is launched, Debug Tool does not locate the source. To avoid this problem, specify the full path name of the source when you compile the program. For example, if you execute the following series of commands, Debug Tool does not find the source because it is located in another directory (/u/myid/mypgm):

1. Change to the directory where your program resides and compile the program.

```
cd /u/myid/mypgm
c++ -g -o "//TEST.LOAD(HELLO)" hello.cpp
```

2. Exit UNIX System Services and return to the TSO READY prompt.

3. Launch the program with the TEST run-time option.

```
call TEST.LOAD(HELLO) 'test/'
```

Debug Tool finds the source if you change the compile command to:

```
c++ -g -o "//TEST.LOAD(HELLO)" /u/myid/mypgm/hello.cpp
```

The same restriction applies to programs that you compile to run in a CICS environment.

Rules for the placement of hooks in functions and nested blocks

The following rules apply to the placement of hooks for functions and nested blocks:

- The hook for function entry is placed before any initialization or statements for the function.
- The hook for function exit is placed just before actual function return.
- The hook for nested block entry is placed before any statements or initialization for the block.
- The hook for nested block exit is placed after all statements for the block.

Rules for the placement of hooks in statements and path points

The following rules apply to the placement of hooks for statements and path points:

- Label hooks are placed before the code and all other statement or path point hooks for the statement.
- The statement hook is placed before the code and path point hook for the statement.
- A path point hook for a statement is placed before the code for the statement.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 8, "Preparing a C program," on page 37

Related references
z/OS C/C++ User's Guide

Chapter 10. Preparing an assembler program

This chapter describes how to prepare an assembler program that you can debug with Debug Tool's full capabilities. To prepare an assembler program, you must do the following steps:

1. Assemble your program with the proper options.
2. Create the EQALANGX file.
3. Link-edit your program.

If you use Debug Tool Utilities to prepare your assembler program, you can do steps 1 and 2 in one step.

You must have Debug Tool Utilities and Advanced Functions installed on your system to prepare and debug assembler programs.

You can debug an assembler program in remote debug mode only with the Compiled Language Debugger component of WebSphere Studio Enterprise Developer.

Before you begin

When you debug an assembler program, you can use most of the Debug Tool commands. There are three differences between debugging an assembler program and debugging programs written in other programming languages supported by Debug Tool:

- After you assemble your program, you must create a debug information file, also called the EQALANGX file. Debug Tool uses this file to obtain information about your assembler program.
- Debug Tool assumes all compile units are written in some high-level language (HLL). You must inform Debug Tool that a compile unit is an assembler compile unit and instruct Debug Tool to load the assembler compile unit's debug information. Do this by entering the LOADDEBUGDATA (or LDD) command.
- Assembler does not have language elements you can use to write expressions. Debug Tool provides assembler-like language elements you can use to write expressions for Debug Tool commands that require an expression. See *Debug Tool for z/OS Reference and Messages* for a description of the syntax of the assembler-like language.

After you verify that your assembler program meets these requirements, prepare your assembler program by doing the following tasks:

1. "Assembling your program" on page 46.
2. "Creating the EQALANGX file" on page 46.

"Assembling your program and creating EQALANGX" on page 47 describes how to prepare an assembler program by using Debug Tool Utilities.

Assembling your program

If you assemble your program without using Debug Tool Utilities, you must use the High Level Assembler (HLASM) and specify a SYSADATA DD statement and the ADATA option. This causes the assembler to create a SYSADATA file. The SYSADATA file is required to generate the debug information (the EQALANGX file) used by Debug Tool.

Creating the EQALANGX file

To create the EQALANGX file, you use the EQALANGX program. The EQALANGX program shipped as a component of Debug Tool is functionally equivalent to the IDILANGX program shipped as a component of IBM Fault Analyzer. If you have IBM Fault Analyzer installed, you can use the IDILANGX program to create the EQALANGX file, as long as the version of the IDILANGX program is the same as or newer than the EQALANGX program shipped with Debug Tool. To identify the version of the program, do the following steps:

1. Create the EQALANGX file as described in the IBM Fault Analyzer documentation.
2. Look at the first record of the generated EQALANGX file and make a note of the version.
3. Create the EQALANGX file as described in this section.
4. Look at the first record of the generated EQALANGX file.

If you choose to use IDILANGX to create the EQALANGX file, you can skip these instructions. See the IBM Fault Analyzer documentation for instructions on creating the EQALANGX file. To create the EQALANGX files without using Debug Tool Utilities, use JCL similar to the following:

```
//XTRACT EXEC PGM=EQALANGX,REGION=32M,  
// PARM='(ASM ERROR LOUD'  
//STEPLIB DD DISP=SHR,DSN=hlq.SEQAMOD  
//SYSADATA DD DISP=SHR,DSN=yourid.sysadata  
//IDILANGX DD DISP=OLD,DSN=yourid.EQALANGX
```

The following list describes the variables used in this example the parameters you can use with the EQALANGX program:

PARM=

(ASM

Indicates that an assembler module is being processed.

ERROR

This parameter is suggested but optional. If you specify it, additional information is displayed when an error is detected.

LOUD

The LOUD parameter is suggested, but optional. If you specify it, additional informational and statistical messages are displayed.

The messages displayed by specifying the ERROR and LOUD parameters are Write To Operator or Write To Programmer (WTO or WTP) messages. See the *IBM Fault Analyzer for z/OS User's Guide and Reference* for detailed information about the messages and return codes displayed by the IDILANGX program. The EQALANGX program uses the same messages and return codes.

hlq.SEQAMOD

The name of the data set containing the Debug Tool load modules. If the Debug Tool load modules are in a system linklib data set, you can omit the following line:

```
//STEPLIB DD DISP=SHR,DSN=hlq.SEQAMOD
```

yourid.sysadata

The name of the data set containing the SYSADATA output from the assembler. If this is a partitioned data set, the member name must be specified. For information about the characteristics of this data set, see *HLASM Programmer's Guide*.

yourid.EQALANGX

The name of the data set where the EQALANGX debug file is to be placed. This data set must have variable block record format (RECFM=VB) and a logical record length of 1562 (LRECL=1562).

Debug Tool searches for the EQALANGX debug file in a partitioned data set with the name *yourid*.EQALANGX and a member name that matches the name of the first CSECT in the assembly. If you want the member name of the EQALANGX debug file to match the first CSECT in the assembly, you do not need to specify a member name on the DD statement.

Assembling your program and creating EQALANGX

You can assemble your program and create the EQALANGX file at the same time by using Debug Tool Utilities. Do the following:

1. Start Debug Tool Utilities. The Debug Tool Utilities panel is displayed.
2. Select option 1, "Program Preparation". The Debug Tool Program Preparation panel is displayed.
3. Select option 5, "Assemble". The Debug Tool Program Preparation - High Level Assembler panel is displayed. In this panel, specify the name of the source file and the assemble options that are used by High Level Assembler (HLASM) to assemble the program.
If option 5 is not available, contact your system administrator.
4. Press Enter. The High Level Assembler - Verify Selections panel is displayed. Verify that the information on the panel is correct and then press Enter.
5. If any of the output data sets you specified do not exist, you are asked to verify the options used to create them.
6. If you specified that the processing be completed by batch, the JCL created to run the batch job is displayed. Verify that the JCL is correct, type Submit in the command line, press Enter and then press PF3.
7. After the processing is completed, the High Level Assembler - View Outputs panel is displayed. This panel displays the return code of each process completed and enables you to view, edit, or browse the input and output data sets.

To read more information about a field in any panel, place the cursor in the input field and press PF1. To read more information about a panel, place the cursor anywhere on the panel that is not an input field and press PF1.

After you assemble your program and create the EQALANGX file, you can link-edit your program.

Link-editing your program

You can link-edit your program by using your normal link-edit procedures or you can use Debug Tool Utilities by doing the following:

1. From the Debug Tool Program Preparation panel, select option L, "Link Edit". The Debug Tool Program Preparation - Link Edit panel is displayed. In this panel, specify the input data sets and link edit options that you need the linker to use.
2. Press Enter. The Link Edit - Verify Selections panel is displayed. Verify that the information on the panel is correct and then press Enter.
3. If any of the output data sets you specified do not exist, you are asked to verify the options used to create them. Press Enter after you verify the options.
4. If you specified that the processing be completed by batch, the JCL created to run the batch job is displayed. Verify that the JCL is correct and press PF3.
5. After the processing is completed, the Link Edit - View Outputs panel is displayed. This panel displays the return code of each process completed and enables you to view, edit, or browse the input and output data sets.

To read more information about a field in any panel, place the cursor in the input field and press PF1. To read more information about a panel, place the cursor anywhere on the panel that is not an input field and press PF1.

After you link-edit your program, you can run your program and start Debug Tool.

Chapter 11. Preparing a DB2 program

There are no special coding techniques for any DB2 programs you might want to debug using Debug Tool.

To communicate with DB2, you should:

- Delimit SQL statements with EXEC SQL and END-EXEC statements
- Declare SQLCA in working storage
- Declare the host variables
- Code the appropriate SQL statements
- Test the DB2 return codes

Program preparation includes the DB2 precompiler, the compiler, the prelinker, the linkage editor, and DB2 bind. The following files must be retained in a permanent data set for Debug Tool to read when you debug your program:

- For COBOL and PL/I, the program listing.
- For COBOL, the separate debug file.
- For C, C++, VisualAge PL/I and Enterprise PL/I, the program source file.

Note: For C, C++, and Enterprise PL/I, it is the input to the compiler (the output from the DB2 precompiler) that needs to be retained.

Refer to the following sections for more information related to the material discussed in this section.

Related references

DB2 UDB for OS/390 Application Programming and SQL Guide

Precompiling DB2 programs for debugging

Before your program can be compiled, the SQL statements must be prepared using the DB2 precompiler. No special preparations are needed in the precompile step to use Debug Tool.

When debugging a program containing SQL, keep the following in mind:

- The SQL preprocessor replaces all the SQL statements in the program with host language code. The modified source output from the preprocessor contains the original SQL statements in comment form. For this reason, the source or listing view displayed during a debugging session can look very different from the original source.
- The host language code inserted by the SQL preprocessor starts the SQL access module for your program. You can halt program execution at each call to a SQL module and immediately following each call to a SQL module, but the called modules cannot be debugged.

Refer to the following sections for more information related to the material discussed in this section.

Related references

DB2 UDB for OS/390 Application Programming and SQL Guide

Compiling DB2 programs for debugging

You must use the output from the DB2 precompiler as input to the compiler.

Before using Debug Tool, you must prepare your program by compiling at least one part of it with the TEST compiler option.

Important: Ensure that your source (if you are working with C, C++, or Enterprise PL/I), separate debug file (if you are working with Enterprise COBOL), or listing (if you are working with COBOL or non-Enterprise PL/I) is stored in a permanent data set that is available to Debug Tool.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 4, "Planning your debug session and collecting resources," on page 21

Related references

Appendix F, "Syntax of the TEST Compiler option," on page 337

Linking DB2 programs for debugging

To debug DB2 programs, you must link the output from the compiler into your program load library. You can include the user run-time options module, CEEUOPT, by doing the following:

1. Find the user run-time options program CEEUOPT in the Language Environment SCEESAMP library.
2. Change the NOTEST parameter into the desired TEST parameter. For example:

```
old:  NOTEST=(ALL,*,PROMPT,INSPREF),
new:  TEST=(,*,;,*),
```

For remote debug mode only

```
TEST=(,.,TCPIP&&9.24.104.79%8001:*)
```

Note: Double ampersand is required.

For full-screen mode through a VTAM terminal only

```
Test=(,.,MFI%TCP00001:)
```

3. Assemble the CEEUOPT program and keep the object code.
4. Link-edit the CEEUOPT object code with any program to start Debug Tool.

The modified assembler program, CEEUOPT, is shown below.

```
*/*****/
*/ LICENSED MATERIALS - PROPERTY OF IBM */
*/ */ */
*/ 5694-A01 */
*/ */ */
*/ (C) COPYRIGHT IBM CORP. 1991, 2001 */
*/ */ */
*/ US GOVERNMENT USERS RESTRICTED RIGHTS - USE, */
*/ DUPLICATION OR DISCLOSURE RESTRICTED BY GSA ADP */
*/ SCHEDULE CONTRACT WITH IBM CORP. */
*/ */ */
*/ STATUS = HLE7705 */
*/*****/
CEEUOPT CSECT
CEEUOPT AMODE ANY
CEEUOPT RMODE ANY
CEEUOPT TEST=(,*,;,*)
END
```

The user run-time options program can be assembled with predefined TEST run-time options to establish defaults for one or more applications. Link-editing an application with this program results in the default options when that application is started.

If your system programmer has not already done so, include all the proper libraries in the SYSLIB concatenation. For example, the ISPLOAD library for ISPLINK calls, and the DB2 DSNLOAD library for the DB2 interface modules (DSNxxxx).

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 17, “Starting Debug Tool from a program,” on page 79

Binding DB2 programs for debugging

Before you can run your DB2 program, you must run a DB2 bind in order to bind your program with the relevant DBRM output from the precompiler step. No special requirements are needed for Debug Tool.

Chapter 12. Preparing a DB2 stored procedures program

The DB2 administrator must define the address space where the stored procedure runs. This can be a DB2 Address Space or a Workload Manager (WLM) Address Space. This address space is assigned a name which is used to define the stored procedure to DB2. In the JCL for the DB2 or WLM address space, verify that the following data sets are defined in the STEPLIB concatenation and have the appropriate RACF Read authorization for programs to access them:

- LOADLIB for the stored procedure
- SEQAMOD for Debug Tool
- SCEERUN for Language Environment

After updating the JCL, the DB2 administrator must recycle the DB2 or WLM address space so that these updates take effect.

To debug a stored procedure, you must compile it with the TEST compiler option and run with the TEST run-time option. If the stored procedure is defined as Type=SUB, the following considerations apply:

- You cannot use the Dynamic Debug facility. If you have the facility installed, use the SET DYNDEBUG OFF command as the first command at the start of your debug session.
- CEEUOPTS is ignored by Language Environment.

If you are going to debug the stored procedure while another user runs it, do the following tasks:

- Compile the stored procedure with the TEST(ALL,SYM) compiler option. Do not compile it with the TEST(NONE,SYM) compiler option.
- You cannot use the Dynamic Debug facility. If you have the facility installed, enter the SET DYNDEBUG OFF command as the first command at the start of your debug session.
- See *DB2 Application Programming and SQL Guide* for information on running a stored procedure concurrently.

The TEST runtime options must be defined to the RUNOPTS field of the DB2 catalog by using the appropriate DB2 SQL commands. In the following example, the stored procedure is a COBOL program called SPROC1 of Type SUB that runs in a WLM address space called WLMENV1. The stored procedures are debugged in remote mode.

```
create procedure sprocl
  language cobol
  external name sprocl
  parameter style general
  wlm environment wlmenv1
  run options 'TEST(,,,TCP/IP&9.112.27.99%8001:*)'
  program type sub;
```

To verify that the stored procedure is defined correctly, use the following SQL SELECT command on the appropriate DB2 table:

```
select * from sysibm.sysroutines;
```

If the definition is not correct, use the following SQL command to modify the stored procedure:

```
alter procedure sprocl run options 'TEST(,,,TCPIP&9.112.27.21%8001:*)';
```

Refer to the following sections for more information related to the material discussed in this section.

Related references

DB2 UDB for OS/390 Application Programming and SQL Guide

Chapter 13. Preparing a CICS program

To prepare a CICS program for debugging, you must do the following tasks:

1. Complete the program preparation tasks for assembler, C, C++, COBOL, or PL/I, as described in the sections listed under **Related tasks**.
2. If you are using debugging profiles to indicate which programs to debug, choose one of the following CICS transactions to manage your debugging profiles:
 - If you are using versions of CICS earlier than CICS Transaction Server for z/OS Version 2 Release 3, use DTCN to manage debugging profiles. Link-edit EQADCCXT into the CICS program that you want to debug. This step is required only for C/C++ programs and all PL/I programs, except PL/I programs compiled in the following environment:
 - Enterprise PL/I for z/OS Version 3 Release 4 with the PTF for APAR PK03264 applied
 - Language Environment Version 1 Release 3 or later, with the PTF for APAR PK03093 applied
 - If you are using CICS Transaction Server for z/OS Version 2 Release 3 or later, you can use either CADP or DTCN to manage debugging profiles. If you use CADP, you do not need to link-edit EQADCCXT into the CICS program that you want to debug. You cannot use both CADP and DTCN; you must choose only one.
3. Create and store a profile that specifies the combination of resource IDs that you want to debug.
4. Run your program.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 5, “Preparing a COBOL program,” on page 25

Chapter 7, “Preparing a PL/I program,” on page 33

Chapter 8, “Preparing a C program,” on page 37

Chapter 9, “Preparing a C++ program,” on page 41

Chapter 10, “Preparing an assembler program,” on page 45

Link-editing EQADCCXT into your program

Debug Tool provides an Language Environment CEEBXITA assembler exit called EQADCCXT to help you activate, by using the DTCN transaction, a debugging session under CICS . You do not need to use this exit if you are running either of the following options:

- You are running under CICS Transaction Server for z/OS Version 2 Release 3 or later and you use the CADP transaction to define debug profiles.
- You are using the DTCN transaction and you are debugging COBOL programs or PL/I programs compiled with the following environment:
 - Enterprise PL/I for z/OS Version 3 Release 4 with the PTF for APAR PK03264 applied
 - Language Environment Version 1 Release 3 or later, with the PTF for APAR PK03093 applied

If you activate a debug session by using DTCN and you are debugging a C, C++, or PL/I programs, you need to link the EQADCCXT exit into the main load module of the program, with the exception of the following PL/I programs:

- Enterprise PL/I for z/OS Version 3 Release 4 with the PTF for APAR PK03264 applied
- Language Environment Version 1 Release 3 or later, with the PTF for APAR PK03093 applied

When you use EQADCCXT, be aware of the following conditions:

- If your site does not use an Language Environment assembler exit (CEEBXITA), then link-edit member EQADCCXT, which contains the CSECT CEEBXITA and is in library *hlq.SEQAMOD*, into your main program.
- If your site uses an existing CEEBXITA, the EQADCCXT exit provided by Debug Tool must be merged with it. The source for EQADCCXT is in *hlq.SEQASAMP(EQADCCXT)*. Link the merged exit into your main program.

After you link-edit your program, use the DTCN transaction to create a profile that specifies the combination of resource IDs that you want to debug. See “Creating and storing a DTCN profile.”

Creating and storing a DTCN profile

The DTCN transaction stores one profile for each DTCN terminal in a repository. Each profile is retained in the repository until one of the following events occurs:

- The profile is explicitly deleted by the terminal that entered it.
- DTCN detects that the terminal which created the profile has been disconnected.
- The CICS region is terminated.

To create and store a DTCN profile, do the following steps:

1. Log on to a CICS terminal and enter the transaction ID **DTCN**. The DTCN transaction displays the main DTCN screen, Debug Tool CICS Control - Primary Menu, shown below.

DTCN		Debug Tool CICS Control - Primary Menu		S07CICPN	
Select the combination of resources to debug (see Help for more information)					
Terminal Id	==> 0077				
Transaction Id	==>				
Program Id(s)	==>	==>	==>	==>	==>
User Id	==> CICSUSER				
NetName	==>				
Select type and ID of debug display device					
Session Type	==> TCP		MFI, TCP		
Port Number	==> 8001		TCP Port		
Display Id	==> 9.30.60.120				
Connection Type	==> SINGLE		SINGLE / MULTIPLE		
Generated String: TEST(ALL,,PROMPT,'TCPIP&9.30.60.120%8001:')					
Repository String: TEST(ALL,,PROMPT,'TCPIP&9.30.60.120%8001:')					
PF1=HELP 2=GHELP 3=EXIT 4=SAVE 6=DELETE 7=SHOW 9=OPTIONS					

Some of the entry fields are filled in with default values that start Debug Tool, in full-screen mode, for tasks running on this terminal. If you do not want to

change the defaults, you can skip the next two steps and proceed to step 4 on page 59. If you want to change the settings on this panel, continue to the next step.

2. Specify the combination of resource IDs that you want to debug.

Terminal Id

Specify the CICS terminal to debug. By default, this ID is set to the terminal that is currently running DTCN. If the DTCNFORCETERMID option in EQAOPTS is set to YES, this field must be specified. See *Debug Tool for z/OS Customization Guide* for a description of these options.

Transaction Id

Specify the CICS transaction to debug. If you specify a transaction ID without any other resource, Debug Tool is started **every** time any of the following situations occurs:

- You run the transaction.
- The first program run by the transaction is started.
- Any other user runs the transaction.
- Any enabled DFH* module is the first program run by the transaction.

To start Debug Tool at the desired program that the transaction runs, specify the program name in the Program Id(s) field. If the DTCNFORCETRANID option in EQAOPTS is set to YES, this field must be specified. See *Debug Tool for z/OS Customization Guide* for a description of these options.

Program Id(s)

Specify the program or programs that you want to debug. You can specify any of the following programs:

- Any CICS program if it is invoked as an Language Environment enclave or over a CICS Link Level. This includes the following types of programs:
 - The initial program in a transaction
 - A program invoked by CICS LINK or XCTL
- Any COBOL program, even if it is a nested program or a subprogram within a composite load module, invoked by a static or dynamic CALL.
- Any Enterprise PL/I for z/OS Version 3 Release 4 program (with the PTF for APAR PK03264 applied) running with Language Environment Version 1 Release 3 or later (with the PTF for APAR PK03093 applied), even if it is a nested program or a subprogram within a composite load module, invoked as a static or dynamic CALL.

Specifying a CICS program in the Program Id(s) field is similar to setting a breakpoint by using the AT ENTRY command and Debug Tool will stop each time the program is entered.

If Debug Tool is already running and it cannot find the separate debug file, then Debug Tool does not stop at the CICS program specified in the Program Id(s) field. Use the AT APPEARANCE or AT ENTRY command to stop at this CICS program.

If the DTCNFORCEPROGID option in EQAOPTS is set to YES, this field must be specified. See *Debug Tool for z/OS Customization Guide* for a description of these options.

User Id

Specify the CICS user ID to debug. All programs that are run by this user will start Debug Tool. If the DTCNFORCEUSERID option in EQAOPTS is set to YES, this field must be specified. See *Debug Tool for z/OS Customization Guide* for a description of these options.

NetName

Specify the four character name of a CICS terminal or a CICS system that you want to use to run your debugging session. This name is used by VTAM to identify the CICS terminal or system. If the DTCNFORCENETNAME option in EQAOPTS is set to YES, this field must be specified. See *Debug Tool for z/OS Customization Guide* for a description of these options.

For more information about these fields, place the cursor next to the field and press PF1 to display the online help.

3. Specify the type of debugging and the ID of the display device.

Session Type

Select one of the following options:

- | | |
|------------|---|
| MFI | Indicates that Debug Tool initializes on a 3270 type of terminal. |
| TCP | Indicates that you want to interact with Debug Tool from your workstation using TCP/IP and a remote debugger. |

Port Number

Specifies the TCP/IP port number that is listening for debug sessions on your workstation. By default, IBM Distributed Debugger uses port 8000 and Compiled Language Debugger component of WebSphere Studio Enterprise Developer uses port 8001.

Display Id

Identifies the target destination for Debug Tool information. Depending on the session type that you've selected, the display ID is one of the following:

- If you selected MFI, the display ID is a CICS 3270 terminal ID. This ID is set by default to the terminal ID that is currently running DTCN, but you can change this to direct MFI screens to a different CICS terminal.
- If you selected TCP, enter either the IP address or host name of the workstation that will display the debug screens. For the debug session to start, the appropriate software must be running on that workstation.

Connection Type

Specifies whether you are using a single or multiple socket connection to the workstation. If you are using a version of the Distributed Debugger that is version 9.2 or Compiled Language Debugger component of WebSphere Studio Enterprise Developer, we recommend you specify a single socket connection.

If you are using a version of the Distributed Debugger that is earlier than version 9.2 (copyright date 2003/10/19), we recommend you specify a multiple socket connection. The early versions of the

Distributed Debugger shipped with the VisualAge family of products and C/C++ Productivity Tools for OS/390.

- Specify the debugging options by pressing PF9 to display the secondary options menu, shown below.

DTCN	Debug Tool CICS Control - Menu 2	S07CICPD
Select Debug Tool options		
Test Option	==> TEST	Test/Notest
Test Level	==> ALL	All/Error/None
Commands File	==> *	
Prompt Level	==> PROMPT	
Preference File	==> *	
Any other valid Language Environment options		
==>		
PF1=HELP 2=GHELP 3=RETURN		

Some of the entry fields are filled in with default values that start Debug Tool, in full-screen mode, for tasks running on this terminal. If you do not want to change the defaults, you can skip the rest of this step and proceed to step 5. If you want to change the settings on this panel, continue with this step.

Test Option

TEST/NOTEST specifies the conditions under which Debug Tool assumes control during the initialization of your application.

Test Level

ALL/ERROR/NONE specifies what conditions need to be met for Debug Tool to gain control.

Command File

A valid fully qualified data set name that specifies the primary commands file for this run.

Note: Do not enclose the name of the data set in single or double quotes.

Prompt Level

Specifies whether Debug Tool is started at Language Environment initialization.

Preference File

A valid fully qualified data set name that specifies the preference file to be used. Do not enclose the name of the data set in single or double quotes.

Any other valid Language Environment Options

You can change any Language Environment option that your site has defined as overrideable except the STACK option. For additional information about Language Environment options, see *z/OS Language Environment Programming Reference* or contact your CICS system programmer.

- Press PF3 to return to the main DTCN panel.
- Press PF4 to save the profile. DTCN performs data verification on the data that you entered in the DTCN panel. When DTCN discovers an error, it places the cursor in the erroneous field and displays a message. You can use context-sensitive help (PF1) to find what is wrong with the input.

Now, any tasks that run in the CICS system and match the resource IDs that you specified in the previous steps will start Debug Tool.

To display all of the active DTCN profiles in the CICS region, press PF7. The Debug Tool CICS Control - All Sessions screen displays, shown below.

DTCN	Debug Tool CICS Control - All Sessions						S07CICPL
Overtime "_" with a "D" to delete a profile.							
	Owner	Term	Tran	User	Netname	Applid	Options String
-	0070	0070	TRN1	USER1	0072	S07CICPL	TEST(ALL,'*',PROMPT,'MFI%0070
		Program(s)		CIC9060	CS9060	CBLAC?3	*9361
PF1=HELP 2=GHELP 3=RETURN 7=BACK 8=FORWARD							

The column titles are defined below:

Owner

The ID of the terminal that created the profile by using DTCN.

Term The value that was entered on the main DTCN screen in the **Terminal Id** field.

Tran The value that was entered on the main DTCN screen in the **Transaction Id** field.

User The value that was entered on the main DTCN screen in the **User Id** field.

Netname

The value the entered on the main DTCN screen in the **Netname** field.

Applid

The application identifier associated with this profile.

Options String

The value of **Repository String** field on the main DTCN screen; it's created based on the values that the user enters in the other fields.

Program(s)

The values that were entered on the main DTCN screen in the **Program Ids** field.

DTCN also reads the Language Environment NOTEST option supplied to the CICS region in CEECOPT or CEEROPT. You can supply suboptions, such as the name of a preference file, with the NOTEST option to supply additional defaults to DTCN.

Sharing DTCN repository profile items among CICS systems

The DTCN repository is a CICS temporary storage queue, named EQADTCN2. If you want to share the repository among CICS systems, define the queue as REMOTE in your CICS temporary storage tables (TST). This setting stores a profile item in one CICS system, and makes it readable to another system.

Using CADP to manage debugging profiles

CICS Transaction Server for z/OS Version 2 Release 3 introduces the following two features:

- A new utility transaction, called CADP, to manage debugging profiles. If you use CADP, you cannot use DTCN.
- A new system initialization parameter called DEBUGTOOL. To use the CADP transaction, the DEBUGTOOL system initialization parameter option must be set to YES.

See *CICS Supplied Transactions* for information about the CADP utility transaction.
See *CICS Application Programming Guide* for information about debugging profiles.

Starting Non-Language Environment Debug Tool under CICS

You can start Debug Tool to debug a program that does not run in the Language Environment run time by using the existing debug profile maintenance transactions DTCN and CADP. You must use DTCN with versions of CICS prior to CICS Transaction Server for z/OS Version 2 Release 3.

To debug CICS non-Language Environment programs, the Debug Tool non-Language Environment exits must have been previously started.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Debug Tool for z/OS Customization Guide

Passing run-time parameters into the non-Language Environment debug session on startup

When you define your debugging profile using the DTCN Options Panel (PF9) or the CADP Create/Modify Debugging Profile Panel, you can pass a limited set of run-time options that will take effect in your non-Language Environment debugging session. These run-time options and their settings include the following:

- TEST/NOTEST: must be TEST
- TEST LEVEL: must be ALL or ERROR
- Commands file
- Prompt Level: must be PROMPT
- Preference file
- You can also specify the following runtime options in a TEST string:
 - NATLANG: to specify the National Language used to communicate with Debug Tool
 - COUNTRY: to specify a Country Code for Debug Tool
 - TRAP: to specify whether Debug Tool is to intercept Abends

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Chapter 14. Preparing an IMS program

If you have Debug Tool Utilities and Advanced Functions installed on your system, you can use Debug Tool Utilities to help you prepare and start your IMS programs. Do the following tasks to prepare your IMS program:

1. Compile and link your IMS program by using the Program Preparation tool in Debug Tool Utilities. Your program must be compiled with the TEST compiler option. Appendix C, “Examples: Preparing programs and modifying setup files with Debug Tool Utilities,” on page 327 describes how to compile and link sample programs provided by Debug Tool. You can study these examples to guide you through the compilation and linking process of your program.

For IMS Transaction Manager (TM) programs running in IMS Version 8, you do not have to link the CEEUOPT load module to obtain information about the TEST run-time options. You can specify the transaction settings and TEST run-time options to use to run your program by using the Manage IMS Programs tool in Debug Tool Utilities. See “Setting up the run-time options for your IMS Version 8 TM program by using Debug Tool Utilities” on page 64 for more information on how to do this task.

For IMS batch programs, you must link the CEEUOPT load module to obtain information about the TEST run-time options. See “Linking IMS programs for debugging” on page 65 for more information on how to do this task.

2. Create and customize a setup file for your IMS Batch Messaging Process (BMP) program by using the Manage IMS Programs tool in Debug Tool Utilities. The setup file contains information about how to create a custom region and it has STEPLIB concatenation statements that reference the data sets for your IMS program’s load module and the Debug Tool load module. See “Creating setup file for your IMS program by using Debug Tool Utilities” on page 64 for more information on how to do this task.

You can also create and customize a setup file for creating a private message region that you can use to test your IMS Message Processing Program (MPP) program. Creating a private message region with class X allows you to test your IMS program run by transaction X and reduce the risk of interfering with other regions being used by other IMS programs. See “Creating setup file for your IMS program by using Debug Tool Utilities” on page 64 for more information on how to do this task.

If you do not have Debug Tool Utilities and Advanced Functions installed on your system, you can continue to compile, link, and start your IMS program by using your site procedures. Remember the following points:

- Your program must be compiled with the TEST compiler option. Use the default options to gain maximum debugging facilities.
- Ensure that your source (if you are working with C, C++, or Enterprise PL/I), listing (if you are working with COBOL or PL/I), or separate debug file (if you are working with COBOL) is stored in a permanent data set that is available to Debug Tool.
- Ensure that you do the tasks described in “Linking IMS programs for debugging” on page 65.

For IMS TM programs running in IMS Version 8, you do not have to link the CEEUOPT load module to obtain information about the TEST run-time options. You can specify the transaction settings and TEST run-time options to use to run

your program by using IMS Version 8 commands. See *IMS Version 8 Command Reference* for more information on how to do this task

Creating setup file for your IMS program by using Debug Tool Utilities

To create a setup file for your IMS program by using Debug Tool Utilities, do the following steps:

1. Start Debug Tool Utilities. If you do not know how to start Debug Tool Utilities, see “Starting Debug Tool Utilities” on page 9.
2. In the Debug Tool Utilities panel (EQA@PRIM), type 4 in the Option line and press Enter.
3. In the Manage IMS Programs panel (EQAPRIS), type 2 in the Option line and press Enter.
4. In the Create Private Message Regions - Edit Setup File panel (EQAPFORA), type in the information to create a new setup file or edit an existing setup file. Press Enter.

Create a private message region to customize your application or Debug Tool libraries while you debug your application so that you do not impact other user’s activities. Consult your system administrator for authorization and rules regarding the creation of private message regions.

After you specify the setup information required to run your IMS program, you can specify the information needed to create a private message region you can use to test your IMS program or specify how to run a BMP program. To specify this setup information, do the following steps:

5. In the Edit Setup File panel (EQAPFORI), type in the information to start IMS batch processor. Type a forward slash (/) in the field Enter / to modify parameters, then press Enter to modify parameters for the batch processor.
6. In the Parameters for IMS Procedures panel (EQAPRIPM), use one of the following values in the TYPE field to indicate which action you want done:

- MSG to start a private message region.
- BMP to run a BMP program.

Enter other parameters as needed. Press PF1 for information about the parameters.

7. After you type in the specifications, you can submit your job for processing by pressing PF10.

Setting up the run-time options for your IMS Version 8 TM program by using Debug Tool Utilities

To specify the transaction settings and TEST run-time options for your IMS program, do the following:

1. From the main Debug Tool Utilities panel (EQA@PRIM), type 4 in the Option line and press Enter.
2. In the Manage IMS Programs panel (EQAPRIS), type 1 in the Option line and press Enter.
3. In the Manage LE Runtime Options in IMS panel (EQAPRI), type in the IMSplex ID and optional qualifiers. Debug Tool Utilities uses this information to search through the IMS LE run-time parameter repository and find the entries that most closely match the information you typed in. You can use wild cards (* and %) to increase the chances of a match. After you type in your search criteria, press Enter.

4. In the Edit LE Runtime Options Entries in IMS panel (EQAPRIM), a table displays all the entries found in the IMS LE run-time parameter repository that most closely match your search criteria. You can do the following tasks in this panel:
 - Delete an entry.
 - Add a new entry.
 - Edit an existing entry.
 - Copy an existing entry.

For more information about a command or field, press PF1 to display a help panel.
5. After you finish making your changes, press PF3 to save your changes and close the panel that is displayed. If necessary, press the PF3 repeatedly to close other panels until you reach the Manage IMS Programs panel (EQAPRIS).

Linking IMS programs for debugging

When you link your IMS TM Version 8 program, you can manage the TEST run-time options without linking in a copy of CEEUOPT. For instructions on managing the TEST run-time options, see “Setting up the run-time options for your IMS Version 8 TM program by using Debug Tool Utilities” on page 64.

When you link your IMS batch program or IMS TM Version 7 or earlier program, you must include a run-time options module in your program link. They must be coded and assembled in a user-defined run-time option module. For instructions on how to create the CEEUOPT run-time options module using the CEEXOPT macro, follow the steps in “Linking DB2 programs for debugging” on page 50.

For COBOL programs using IMS, include the IMS interface module DFSLI000 from the IMS RESLIB library.

Part 3. Starting Debug Tool

Chapter 15. Starting Debug Tool from the Debug Tool Utilities

The 'Manage and Use Debug Tool Setup Files' function (also called Debug Tool Setup Utilities or DTSU) in Debug Tool Utilities helps you manage setup files which store the following information:

- file allocation statements
- run-time options
- program parameters
- the name of your program

Then you use the setup files to run your program in foreground or batch. The Debug Tool Setup Utility (DTSU) RUN command performs the file allocations and then starts the program with the specified options and parameters in the foreground. The DTSU SUBMIT command submits a batch job to start the program.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Creating the setup file"

"Editing an existing setup file"

"Saving your setup file" on page 72

"Starting your program" on page 72

Creating the setup file

You can have several setup files, but you must create them one at a time. To create a setup file, do the following steps:

1. From the Debug Tool Utilities panel, select the **Manage and Use Debug Tool Setup Files** option.
2. In the Debug Tool Foreground – Edit Setup File panel, type the name of the new setup file in the **Setup File Library** or **Other Data Set Name** field. Do not specify a member name if you are creating a sequential data set. If you are creating a setup file for a DB2 program, select the **Initialize New setup file for DB2** field. Press Enter.
3. A panel similar to the ISPF 3.2 "Allocate New Data Set" panel appears. You can modify the default allocation parameters. Enter the END command or press PF3 to continue.
4. The Edit – Edit Setup File panel appears. You can enter file allocation statements, run-time options, and program parameters.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Entering file allocation statements, run-time options, and program parameters" on page 70

Editing an existing setup file

You can have several setup files, but you can edit only one file at a time. To edit an existing setup file, do the following steps:

1. From the Debug Tool Utilities panel, select the **Manage and Use Debug Tool Setup Files** option.
2. In the Debug Tool Foreground – Edit Setup File panel, type the name of the existing setup file in the **Setup File Library** or **Other Data Set Name** field. Press Enter to continue.
3. The Edit – Edit Setup File panel appears. You can modify file allocation statements, run-time options, and program parameters.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Entering file allocation statements, run-time options, and program parameters”

Copying information into a setup file from an existing JCL

You can enter the COPY command to copy an EXEC statement and its associated DD statements from another data set containing JCL.

Entering file allocation statements, run-time options, and program parameters

The top part of the Edit–Setup File panel contains the name of the program (load module) that you want to run and the run-time parameter string. If the setup file is for a DB2 program, the panel also contains fields for the DB2 System identifier and the DB2 plan. The bottom part of the Edit–Setup File panel contains the file allocation statements. This part of the panel is similar to an ISPF edit panel. You can insert new lines, copy (repeat) a line, delete a line, and type over information on a line.

To modify the name of the load module, type the new name in the **Load Module Name** field.

To modify the parameter string:

1. Select the format of the parameter string and whether the program is to start in the Language Environment. OS/VS COBOL programs do not run in Language Environment. If you are debugging an OS/VS COBOL, select the non-Language Environment option.
2. Enter the parameter string in one of the following ways:
 - Type the parameter string in the **Enter / to modify parameters** field.
 - Type a slash ("/") before the **Enter / to modify parameters** field and press Enter. The Debug Tool Foreground - Modify Parameter String panel appears. Define your run-time options and suboptions by doing the following steps:
 - a. Define the TEST run-time option and its suboptions.
 - b. Enter any Language Environment or Debug Tool run-time options and other program parameters.
 - c. Press PF3. DTSU creates the parameter string from the options that you specified and puts it in the **Enter / to modify parameters** field.

In the file allocation section of the panel, each line represents an element of a DD name allocation or concatenation. The statements can be modified, copied, deleted, and reordered.

To modify a statement, do one of the following steps:

- Modify the statement directly on the Edit – Edit Setup File panel:
 1. Move your cursor to the statement you want to modify.
 2. Type the new information over the existing information.
 3. Press Enter.
- Modify the statement by using a select command:
 1. Move your cursor to the statement you want to modify.
 2. Type one of the following select commands:
 - SA - Specify allocation information
 - SD - Specify DCB information
 - SS - Specify SMS information
 - SP - Specify protection information
 - SO - Specify sysout information
 - SX - Specify all DD information by column display
 - SZ - Specify all DD information by section display
 3. Press Enter.

To copy a statement, do the following steps:

1. Move your cursor to the **Cmd** field of the statement you want to copy.
2. Type R and press Enter. The statement is copied into a new line immediately following the current line.

To delete a statement, do the following steps:

1. Move your cursor to the **Cmd** field of the statement you want to delete.
2. Type D and press Enter. The statement is deleted.

To reorder statements in a concatenation, do the following steps:

1. Move your cursor to the sequence number field of a statement you want to move and enter the new sequence number.

To insert a new line, do the following steps:

1. Move your cursor to the **Cmd** field of the line right above the line you want a new statement inserted.
2. Type I and press Enter.
3. Move your cursor to the new line and type in the new information or use one of the Select commands.

The Edit and Browse line commands allow you to modify or view the contents of the data set name specified for DD and SYSIN DD types.

You can use the DDNAME STEPLIB to specify the load module search order.

For additional help, move the cursor to any field and enter the HELP command or press PF1.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Saving your setup file” on page 72

Saving your setup file

To save your information, enter the SAVE command. To save your information in a second data set and continue editing in the second data set, enter the SAVE AS command.

To save your setup file and exit the Edit-Edit Setup File panel, enter the END command or press PF3.

To exit the Edit-Edit Setup File panel without saving any changes to your setup file, enter the CANCEL command or press PF12.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Starting your program"

Starting your program

To perform the allocations and run the program with the specified parameter string, enter the RUN command or press PF4.

To generate JCL from the information in the setup file and then submit to the batch job, enter the SUBMIT command or press PF10.

Chapter 16. Starting Debug Tool by using the TEST run-time option

The instructions in this section apply to programs that run in Language Environment. For programs that do not run in Language Environment, refer to the instructions in “Programs that start outside of Language Environment” on page 92.

To specify how Debug Tool gains control of your application and begins a debug session, you can use the TEST run-time option. The simplest form of the TEST option is TEST with no suboptions specified; however, suboptions provide you with more flexibility. There are four types of suboptions available, summarized below.

test_level

Determines what high-level language conditions raised by your program cause Debug Tool to gain control of your program

commands_file

Determines which primary commands file is used as the initial source of commands

prompt_level

Determines whether an initial commands list is unconditionally run during program initialization

preferences_file

Specifies the session parameter and a file that you can use to specify default settings for your debugging environment, such as customizing the settings on the Debug Tool Profile panel

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 17, “Starting Debug Tool from a program,” on page 79

Related references

“Special considerations while using the TEST run-time option”

Special considerations while using the TEST run-time option

When you use the TEST run-time option, there are several implications to consider, which are described in this section.

Defining TEST suboptions in your program

In C, C++ or PL/I, you can define TEST with suboptions using a #pragma runopts or PLIXOPT string, then specify TEST with no suboptions at run time. This causes the suboptions specified in the #pragma runopts or PLIXOPT string to take effect.

You can change the TEST/NOTEST run-time options at any time with the SET TEST command.

Suboptions and NOTEST

Some suboptions are disabled with NOTEST, but are still allowed. This means you can start your program using the NOTEST option and specify suboptions you might want to take effect later in your debug session. The program begins to run without Debug Tool taking control.

To enable the suboptions you specified with NOTEST, start Debug Tool during your program's run time by using a library service call such as CEETEST, PLITEST, or the `__ctest()` function.

Implicit breakpoints

If the test level in effect causes Debug Tool to gain control at a condition or at a particular program location, an implicit breakpoint with no associated action is assumed. This occurs even though you have not previously defined a breakpoint for that condition or location using an initial command string or a primary commands file. Control is given to your terminal or to your primary commands file.

Primary commands file and USE file

The primary commands file acts as a surrogate terminal. After it is accessed as a source of commands, it continues to act in this capacity until all commands have been run or the application has ended. This differs from the USE file in that, if a USE file contains a command that returns control to the program (such as STEP or G0), all subsequent commands are discarded. However, USE files started from within a primary commands file take on the characteristics of the primary commands file and can be run until complete.

The initial command list, whether it consists of a command string included in the run-time options or a primary commands file, can contain a USE command to get commands from a secondary file. If started from the primary commands file, a USE file takes on the characteristics of the primary commands file.

Running in batch mode

In batch mode, when the end of your commands file is reached, a G0 command is run at each request for a command until the program terminates. If another command is requested after program termination, a QUIT command is forced.

Starting Debug Tool at different points

If Debug Tool is started during program initialization, it is started before all the instructions in the main prolog are run. At that time, no program blocks are active and references to variables in the main procedure cannot be made, compile units cannot be called, and the GOTO command cannot be used. However, references to static variables can be made.

If you enter the STEP command at this point, before entering any other commands, both program and Language Environment initialization are completed and you are given access to all variables. You can also enter all valid commands.

If Debug Tool is started while your program is running (for example, by using a CEETEST call), it might not be able to find all compile units associated with your application. Compile units located in load modules that are not currently active are not known to Debug Tool, even if they were run prior to Debug Tool's initialization.

For example, suppose load module mod1 contains compile units cu1 and cu2, both compiled with the TEST option. The compile unit cu1 calls cux, contained in load module mod2, which returns after it completes processing. The compile unit cu2 contains a call to the CEETEST library service. When the call to CEETEST initializes Debug Tool, only cu1 and cu2 are known to Debug Tool. Debug Tool does not recognize cux.

The initial command string is run only once, when Debug Tool is first initialized in the process.

Commands in the preferences file are run only once, when Debug Tool is first initialized in the process.

Session log

The session log stores the commands entered and the results of the execution of those commands. The session log saves the results of the execution of the commands as comments. This allows you to use the session log as a commands file.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Link-editing EQADCCXT into your program” on page 55

Related references

Debug Tool for z/OS Reference and Messages

Precedence of Language Environment run-time options

The Language Environment run-time options have the following order of precedence (from highest to lowest):

1. Installation options in the CEEDOPT file that were specified as nonoverrideable with the NONOVR attribute.
2. Options specified by the Language Environment assembler user exit. In the CICS environment, Debug Tool uses the DTCN transaction and the customized Language Environment user exit EQADCCXT, which is link-edited with the application. In the IMS Version 8 environment, IMS retrieves the options that most closely match the options in its Language Environment run-time options table. You can edit this table by using Debug Tool Utilities.
3. Options specified at the invocation of your application, using the TEST run-time option, unless accepting run-time options is disabled by Language Environment (EXECOPS/NOEXECOPS).
4. Options specified within the source program (with #pragma or PLIXOPT) or application options specified with CEEUOPT and link-edited with your application.

If the object module for the source program is input to the linkage editor before the CEEUOPT object module, *then* these options override CEEUOPT defaults. You can force the order in which objects modules are input by using linkage editor control statements.

5. Region-wide CICS or IMS options defined within CEEROPT.
6. Option defaults specified at installation in CEEDOPT.
7. IBM-supplied defaults.

Suboptions are processed in the following order:

1. Commands entered at the command line override any defaults or suboptions specified at run time.
2. Commands run from a preferences file override the command string and any defaults or suboptions specified at run time.
3. Commands from a commands file override default suboptions, suboptions specified at run time, commands in a command string, and commands in a preferences file.

Refer to the following sections for more information related to the material discussed in this section.

Related references

z/OS Language Environment Programming Guide

Example: TEST run-time options

The following examples of using the TEST run-time option are provided to illustrate run-time options available for your programs. They do not illustrate complete commands. The complete syntax of the TEST run-time option can be found in the *Debug Tool for z/OS Reference and Messages*.

NOTEST Debug Tool is not started at program initialization. Note that a call to CEETEST, PLITEST, or __ctest() causes Debug Tool to be started during the program's execution.

NOTEST(ALL,MYCMDS,*,*)

Debug Tool is not started at program initialization. Note that a call to CEETEST, PLITEST, or __ctest() causes Debug Tool to be started during the program's execution. After Debug Tool is started, the suboptions specified become effective and the commands in the file allocated to DD name of MYCMDS are processed.

If you specify NOTEST and control has returned from the program in which Debug Tool first became active, you can no longer debug non-Language Environment programs or detect non-Language Environment events.

TEST Specifying TEST with no suboptions causes a check for other possible definitions of the suboption. For example, C and C++ allow default suboptions to be selected at compile time using #pragma runopts. Similarly, PL/I offers the PLIXOPT string. Language Environment provides the macro CEEXOPT. Using this macro, you can specify installation and program-specific defaults.

If no other definitions for the suboptions exist, the IBM-supplied default suboptions are (ALL, *, PROMPT, INSPREF).

TEST(ALL,*,*,*)

Debug Tool is not started initially; however, any condition or an attention in your program causes Debug Tool to be started, as does a call to CEETEST, PLITEST, or __ctest(). Neither a primary commands file nor preferences file is used.

TEST(NONE,,*,*)

Debug Tool is not started initially and begins by running in a "production mode", that is, with minimal effect on the processing of the program. However, Debug Tool can be started using CEETEST, PLITEST, or __ctest().

TEST(ALL,test.scenario,PROMPT,prefer)

Debug Tool is started at the end of environment initialization, but before the main program prolog has completed. The ddname prefer is processed

as the preferences file, and subsequent commands are found in data set `test.scenario`. If all commands in the commands file are processed and you issue a STEP command when prompted, or a STEP command is run in the commands file, the main block completes initialization (that is, its AUTOMATIC storage is obtained and initial values are set). If Debug Tool is reentered later for any reason, it continues to obtain commands from `test.scenario` repeating this process until end-of-file is reached. At this point, commands are obtained from your terminal.

TEST(ALL,,,MFI%F000:)

For CICS dual terminal and CICS batch, Debug Tool is started on the terminal F000 at the end of the environment initialization.

TEST(ALL,,,MFI%TCP00001:)

For environments other than CICS, Debug Tool is started on the terminal associated with the VTAM LU TCP00001. This terminal must be known to VTAM and not in session when Debug Tool is started.

Remote debug mode

If you are working in remote debug mode, that is, you are debugging your host application from your workstation, the following examples apply:

```
TEST(,,,TCPIP&machine.somewhere.something.com%8001:*)
TEST(,,,TCPIP&9.24.104.79%8001:*)
NOTEST(,,,TCPIP&9.24.111.55%8001:*)
```

Refer to the following sections for more information related to the material discussed in this section.

Related references

z/OS Language Environment Programming Guide

Specifying additional run-time options with COBOL II and PL/I programs

There are two additional run-time options that you might need to specify to debug COBOL and PL/I programs: STORAGE and TRAP(ON).

Specifying the STORAGE run-time option

The STORAGE run-time option controls the initial content of storage when allocated and freed, and the amount of storage that is reserved for the "out-of-storage" condition. When you specify one of the parameters in the STORAGE run-time option, all allocated storage processed by the parameter is initialized to that value. If your program does not have self-initialized variables, you must specify the STORAGE run-time option.

Specifying the TRAP(ON) run-time option

The TRAP(ON) run-time option is used to fully enable the Language Environment condition handler that passes exceptions to the Debug Tool. Along with the TEST option, it **must** be used if you want the Debug Tool to take control automatically when an exception occurs. You must also use the TRAP(ON) run-time option if you want to use the GO BYPASS command and to debug handlers you have written. Using TRAP(OFF) with the Debug Tool causes unpredictable results to occur, including the operating system cancelling your application and Debug Tool when a condition,abend, or interrupt is encountered.

Note: This option replaces the OS PL/I and VS COBOL II STAE/NOSTAE options.

Specifying TEST run-time option with #pragma runopts in C and C++

The TEST run-time option can be specified either when you start your program, or directly in your source by using this #pragma:

```
#pragma runopts (test(suboption,suboption...))
```

This #pragma must appear before the first statement in your source file. For example, if you specified the following in the source:

```
#pragma runopts (notest(all,*,prompt))
```

then entered TEST on the command line, the result would be TEST(ALL,*,PROMPT).

TEST overrides the NOTEST option specified in the #pragma and, because TEST does not contain any suboptions of its own, the suboptions ALL, *, and PROMPT remain in effect.

If you link together two or more compile units with differing #pragmas, the options specified with the first compile are honored. With multiple enclaves, the options specified with the first enclave (or compile unit) started *in each new process* are honored.

If you specify options on the command line and in a #pragma, any options entered on the command line override those specified in the #pragma unless you specify NOEXECOPS. Specifying NOEXECOPS, either in a #pragma or with the EXECOPS compiler option, prevents any command line options from taking effect.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

z/OS C/C++ User's Guide

Chapter 17. Starting Debug Tool from a program

The instructions in this section apply to programs that run in Language Environment. For programs that do not run in Language Environment, refer to the instructions in “Programs that start outside of Language Environment” on page 92.

Debug Tool can also be started directly from within your program using one of the following methods:

- Language Environment provides the callable service CEETEST that is started from Language Environment-enabled languages.
- For C or C++ programs, you can use a `__ctest()` function call or include a `#pragma runopts` specification in your program.

Note: The `__ctest()` function is not supported in CICS.

- For PL/I programs, you can use a call to PLITEST or by including a PLIXOPT string that specifies the correct TEST run-time suboptions to start Debug Tool.

If you use these methods to start Debug Tool, you can debug non-Language Environment programs and detect non-Language Environment events only in the enclave in which Debug Tool first appeared and in subsequent enclaves. You cannot debug non-Language Environment programs or detect non-Language Environment events in higher-level enclaves.

To start Debug Tool using these alternatives, you still need to be aware of the TEST suboptions specified using NOTEST, CEEUOPT, or other “indirect” settings.

“Example: using CEETEST to start Debug Tool from C/C++” on page 81

“Example: using CEETEST to start Debug Tool from COBOL” on page 83

“Example: using CEETEST to start Debug Tool from PL/I” on page 84

Related tasks

“Starting Debug Tool with CEETEST”

“Starting Debug Tool with PLITEST” on page 85

“Starting Debug Tool with the `__ctest()` function” on page 86

“Starting Debug Tool by using CEEUOPT” on page 98

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Special considerations while using the TEST run-time option” on page 73

Starting Debug Tool with CEETEST

Using CEETEST, you can start Debug Tool from within your program and send it a string of commands. If no command string is specified, or the command string is insufficient, Debug Tool prompts you for commands from your terminal or reads them from the commands file. In addition, you have the option of receiving a feedback code that tells you whether the invocation procedure was successful.

If you don’t want to compile your program with hooks, you can use CEETEST calls to start Debug Tool at strategic points in your program. If you decide to use this method, you still need to compile your application so that symbolic information is created.

Using CEETEST when Debug Tool is already initialized results in a reentry that is similar to a breakpoint.

The syntax for CEETEST is:

For C and C++

```
►► void CEETEST ( [string_of_commands] , [fc] ) ; ◄◄
```

For COBOL

```
►► CALL "CEETEST" USING string_of_commands , fc ; ◄◄
```

For PL/I

```
►► CALL CEETEST ( [ * string_of_commands ] , [ * fc ] ) ; ◄◄
```

string_of_commands (input)

Halfword-length prefixed string containing a Debug Tool command list, *string_of_commands* is optional.

If Debug Tool is available, the commands in the list are passed to the debugger and carried out.

If *string_of_commands* is omitted, Debug Tool prompts for commands in interactive mode.

For Debug Tool, remember to use the continuation character if your command exceeds 72 characters.

fc (output)

A 12-byte *feedback* code, optional in some languages, that indicates the result of this service.

CEE000

Severity = 0
Msg_No = Not Applicable
Message = Service completed successfully

CEE2F2

Severity = 3
Msg_No = 2530
Message = A debugger was not available

Note: The CEE2F2 feedback code can also be obtained by MVS/JES batch applications. For example, either the Debug Tool environment was corrupted or the debug event handler could not be loaded.

Language Environment provides a callable service called CEEDCOD to help you decode the fields in the feedback code. Requesting the return of the feedback code is recommended.

For C and C++ and COBOL, if Debug Tool was started through CALL CEETEST, the GOTO command is only allowed after Debug Tool has returned control to your program via STEP or GO.

Usage notes

C and C++

Include `leawi.h` header file.

COBOL

Include CEEIGZCT. CEEIGZCT is in the Language Environment SCEESAMP data set.

PL/I Include CEEIBMAW and CEEIBMCT. CEEIBMAW is in the Language Environment SCEESAMP data set.

Batch and CICS nonterminal processes

We strongly recommend that you use feedback codes (fc) when using CEETEST to initiate Debug Tool from a batch process or a CICS nonterminal task; otherwise, results are unpredictable.

“Example: using CEETEST to start Debug Tool from C/C++”

“Example: using CEETEST to start Debug Tool from COBOL” on page 83

“Example: using CEETEST to start Debug Tool from PL/I” on page 84

Related tasks

“Entering multiline commands in full-screen and line mode” on page 205

Related references

z/OS Language Environment Programming Guide

Example: using CEETEST to start Debug Tool from C/C++

The following examples show how to use the Language Environment callable service CEETEST to start Debug Tool from C or C++ programs.

Example 1

In this example, an empty command string is passed to Debug Tool and a pointer to the Language Environment feedback code is returned. If no other TEST run-time options have been compiled into the program, the call to CEETEST starts Debug Tool with all defaults in effect. After it gains control, Debug Tool prompts you for commands.

```
#include <leawi.h>
#include <string.h>
#include <stdio.h>

int main(void) {
    _VSTRING commands;
    _FEEDBACK fc;

    strcpy(commands.string, "");
    commands.length = strlen(commands.string);

    CEETEST(&commands, &fc);
}
```

Example 2

In this example, a string of valid Debug Tool commands is passed to Debug Tool and a pointer to Language Environment feedback code is returned. The call to CEETEST starts Debug Tool and the command string is processed. At statement 23, the values of x and y are displayed in the Log,

and execution of the program resumes. Barring further interrupts, the behavior at program termination depends on whether you have set AT TERMINATION:

- If you have set AT TERMINATION, Debug Tool regains control and prompts you for commands.
- If you have not set AT TERMINATION, the program terminates.

The command LIST(z) is discarded when the command G0 is executed.

Note: If you include a STEP or G0 in your command string, all commands after that are not processed. The command string operates like a commands file.

```
#include <leawi.h>
#include <string.h>
#include <stdio.h>

int main(void) {
    _VSTRING commands;
    _FEEDBACK fc;

    strcpy(commands.string, "AT LINE 23; {LIST(x); LIST(y);} G0; LIST(z)");
    commands.length = strlen(commands.string);
    :
    CEETEST(&commands, &fc);
    :
}
```

Example 3

In this example, a string of valid Debug Tool commands is passed to Debug Tool and a pointer to the feedback code is returned. If the call to CEETEST fails, an informational message is printed.

If the call to CEETEST succeeds, Debug Tool is started and the command string is processed. At statement 30, the values of x and y are displayed in the Log, and execution of the program resumes. Barring further interrupts, the behavior at program termination depends on whether you have set AT TERMINATION:

- If you have set AT TERMINATION, Debug Tool regains control and prompts you for commands.
- If you have not set AT TERMINATION, the program terminates.

```
#include <leawi.h>
#include <string.h>
#include <stdio.h>

#define SUCCESS "\\0\\0\\0\\0"

int main (void) {

    int x,y,z;
    _VSTRING commands;
    _FEEDBACK fc;

    strcpy(commands.string,"AT LINE 30 { LIST(x); LIST(y); } G0;");
    commands.length = strlen(commands.string);
    :
    CEETEST(&commands,&fc);
    :
    if (memcmp(&fc,SUCCESS,4) != 0) {
        printf("CEETEST failed with message number %d\\n",fc.tok_msgno);
        return(2999);
    }
}
```

Example: using CEETEST to start Debug Tool from COBOL

The following examples show how to use the Language Environment callable service CEETEST to start Debug Tool from COBOL programs.

Example 1

A command string is passed to Debug Tool at its invocation and the feedback code is returned. After it gains control, Debug Tool becomes active and prompts you for commands or reads them from a commands file.

```
01 FC.
  02 CONDITION-TOKEN-VALUE.
  COPY CEEIGZCT.
    03 CASE-1-CONDITION-ID.
      04 SEVERITY    PIC S9(4) BINARY.
      04 MSG-NO     PIC S9(4) BINARY.
    03 CASE-2-CONDITION-ID
      REDEFINES CASE-1-CONDITION-ID.
      04 CLASS-CODE PIC S9(4) BINARY.
      04 CAUSE-CODE PIC S9(4) BINARY.
    03 CASE-SEV-CTL  PIC X.
    03 FACILITY-ID   PIC XXX.
  02 I-S-INFO        PIC S9(9) BINARY.
77 Debugger          PIC x(7) Value 'CEETEST'.

01 Parms.
  05 AA              PIC S9(4) BINARY Value 14.
  05 BB              PIC x(14) Value 'SET SCREEN ON;'.

CALL Debugger USING Parms FC.
```

Example 2

A string of commands is passed to Debug Tool when it is started. After it gains control, Debug Tool sets a breakpoint at statement 23, runs the LIST commands and returns control to the program by running the GO command. The command string is already defined and assigned to the variable COMMAND-STRING by the following declaration in the DATA DIVISION of your program:

```
01 COMMAND-STRING.
  05 AA    PIC 99 Value 60 USAGE IS COMPUTATIONAL.
  05 BB    PIC x(60) Value 'AT STATEMENT 23; LIST (x); LIST (y); GO;'.

```

The result of the call is returned in the feedback code, using a variable defined as:

```
01 FC.
  02 CONDITION-TOKEN-VALUE.
  COPY CEEIGZCT.
    03 CASE-1-CONDITION-ID.
      04 SEVERITY    PIC S9(4) BINARY.
      04 MSG-NO     PIC S9(4) BINARY.
    03 CASE-2-CONDITION-ID
      REDEFINES CASE-1-CONDITION-ID.
      04 CLASS-CODE PIC S9(4) BINARY.
      04 CAUSE-CODE PIC S9(4) BINARY.
    03 CASE-SEV-CTL  PIC X.
    03 FACILITY-ID   PIC XXX.
  02 I-S-INFO        PIC S9(9) BINARY.
```

in the DATA DIVISION of your program. You are not prompted for commands.

```
CALL "CEETEST" USING COMMAND-STRING FC.
```

Example: using CEETEST to start Debug Tool from PL/I

The following examples show how to use the Language Environment callable service CEETEST to start Debug Tool from PL/I programs.

Example 1

No command string is passed to Debug Tool at its invocation and no feedback code is returned. After it gains control, Debug Tool becomes active and prompts you for commands or reads them from a commands file.

```
CALL CEETEST(*,*);    /* omit arguments */
```

Example 2

A command string is passed to Debug Tool at its invocation and the feedback code is returned. After it gains control, Debug Tool becomes active and executes the command string. Barring any further interruptions, the program runs to completion, where Debug Tool prompts for further commands.

```
DCL  ch char(50)
      init('AT STATEMENT 10 DO; LIST(x); LIST(y); END; GO;');

DCL  1  fb,
      5  Severity  Fixed bin(15),
      5  MsgNo     Fixed bin(15),
      5  flags,
      8  Case      bit(2),
      8  Sev       bit(3),
      8  Ctrl      bit(3),
      5  FacID     Char(3),
      5  I_S_info  Fixed bin(31);

DCL  CEETEST ENTRY ( CHAR(*) VAR OPTIONAL,
      1  optional ,
      254 real fixed bin(15),    /* MsgSev      */
      254 real fixed bin(15),    /* MSGNUM      */
      254                      /* Flags       */
      255 bit(2),                /* Flags_Case   */
      255 bit(3),                /* Flags_Severity */
      255 bit(3),                /* Flags_Control */
      254 char(3),               /* Facility_ID  */
      254 fixed bin(31) )        /* I_S_Info     */
      options(assembler) ;

CALL CEETEST(ch, fb);
```

Example 3

This example assumes that you use predefined function prototypes and macros by including CEEIBMAW, and predefined feedback code constants and macros by including CEEIBMCT.

A command string is passed to Debug Tool that sets a breakpoint on every tenth executed statement. Once a breakpoint is reached, Debug Tool displays the current location information and continues the execution. After the CEETEST call, the feedback code is checked for proper execution.

Note: The feedback code returned is either CEE000 or CEE2F2. There is no way to check the result of the execution of the command passed.

```
%INCLUDE CEEIBMAW;
%INCLUDE CEEIBMCT;
DCL 01 FC FEEDBACK;
```

```

/* if CEEIBMCT is NOT included, the following DECLARES need to be
   provided: ----- comment start -----

Declare CEEIBMCT Character(8) Based;
Declare ADDR      Builtin;
%DCL FBCHECK ENTRY;
%FBCHECK: PROC( fbtoken, condition ) RETURNS( CHAR );
  DECLARE
    fbtoken CHAR;
    condition CHAR;
  RETURN(' (ADDR('||fbtoken||')->CEEIBMCT = '||condition||')');
%END FBCHECK;
%ACT FBCHECK;
----- comment end ----- */

Call CEETEST('AT Every 10 STATEMENT * Do; Q Loc; Go; End;'||
             'List AT;', FC);

If ~FBCHECK(FC, CEE000)
  Then Put Skip List('——> ERROR! in CEETEST call', FC.MsgNo);

```

Starting Debug Tool with PLITEST

For PL/I programs, the preferred method of Starting Debug Tool is to use the built-in subroutine PLITEST. It can be used in exactly the same way as CEETEST, except that you do not need to include CEEIBMAW or CEEIBMCT, or perform declarations.

The syntax is:

```

▶▶—CALL—PLITEST—└──────────────────────────────────┘;──────────────────────────────────▶▶
                    └(—character_string_expression—)┘

```

character_string_expression

Specifies a list of Debug Tool commands. If necessary, this is converted to a fixed-length string.

Notes:

1. If Debug Tool executes a command in a CALL PLITEST command string that causes control to return to the program (GO for example), any commands remaining to be executed in the command string are discarded.
2. If you don't want to compile your program with hooks, you can use CALL PLITEST statements as hooks and insert them at strategic points in your program. If you decide to use this method, you still need to compile your application so that symbolic information is created.

The following examples show how to use PLITEST to start Debug Tool for PL/I.

Example 1

No argument is passed to Debug Tool when it is started. After gaining control, Debug Tool prompts you for commands.

```
CALL PLITEST;
```

Example 2

A string of commands is passed to Debug Tool when it is started. After gaining control, Debug Tool sets a breakpoint at statement 23, and returns control to the program. You are not prompted for commands. In addition, the List Y; command is discarded because of the execution of the GO command.

```
CALL PLITEST('At statement 23 Do; List X; End; Go; List Y;');
```

Example 3

Variable *ch* is declared as a character string and initialized as a string of commands. The string of commands is passed to Debug Tool when it is started. After it runs the commands, Debug Tool prompts you for more commands.

```
DCL ch Char(45) Init('At Statement 23 Do; List x; End;');  
  
CALL PLITEST(ch);
```

Starting Debug Tool with the `__ctest()` function

You can also use the C and C++ library routine `__ctest()` or `ctest()` to start Debug Tool. Add:

```
#include <ctest.h>
```

to your program to use the `ctest()` function.

Note: If you do not include `ctest.h` in your source or if you compile using the option `LANGVL(ANSI)`, you **must** use `__ctest()` function. The `__ctest()` function is not supported in CICS.

When a list of commands is specified with `__ctest()`, Debug Tool runs the commands in that list. If you specify a null argument, Debug Tool gets commands by reading from the supplied commands file or by prompting you. If control returns to your application before all commands in the command list are run, the remainder of the command list is ignored. Debug Tool will continue reading from the specified commands file or prompt for more input.

If you do not want to compile your program with hooks, you can use `__ctest()` function calls to start Debug Tool at strategic points in your program. If you decide to use this method, you still need to compile your application so that symbolic information is created.

Using `__ctest()` when Debug Tool is already initialized results in a reentry that is similar to a breakpoint.

The syntax for this option is:

```
(1)  
►►—int—__ctest——(—char—*char_str_exp—)—;—————►►
```

Notes:

1 The syntax for `ctest()` and `__ctest()` is the same.

char_str_exp

Specifies a list of Debug Tool commands.

The following examples show how to use the `__ctest()` function for C and C++.

Example 1

A null argument is passed to Debug Tool when it is started. After it gains control, Debug Tool prompts you for commands (or reads commands from the primary commands file, if specified).

```
__ctest(NULL);
```

Example 2

A string of commands is passed to Debug Tool when it is started. At statement 23, Debug Tool lists *x* and *y*, then returns control to the program. You are not prompted for commands. In this case, the command `list z;` is never executed because of the execution of the command `G0`.

```
__ctest("at line 23 {"  
        "  list x;"  
        "  list y;"  
        "}"  
        "go;"  
        "list z;");
```

Example 3

Variable *ch* is declared as a pointer to character string and initialized as a string of commands. The string of commands is passed to Debug Tool when it is started. After it runs the string of commands, Debug Tool prompts you for more commands.

```
char *ch = "at line 23 list x;";  
:  
__ctest(ch);
```

Example 4

A string of commands is passed to Debug Tool when it is started. After Debug Tool gains control, you are not prompted for commands. Debug Tool runs the commands in the command string and returns control to the program by way of the `G0` command.

```
#include <stdio.h>  
#include <string.h>  
  
char *ch = "at line 23 printf(\"x.y is %d\\n\", x.y); go;";  
char buffer[35.132];  
  
strcpy(buffer, "at change x.y;");  
  
__ctest(strcat(buffer, ch));
```

Chapter 18. Starting Debug Tool for batch or TSO programs

This section describes how to start Debug Tool to debug programs that run in the following situations:

- Programs that start in Language Environment
- Programs that start outside of Language Environment

Programs that start in Language Environment

You have two choices to start Debug Tool under MVS in TSO:

- You can follow the instructions outlined in this section. The instructions describe how to allocate all the files you need to start your debug session and how to start your program with the proper parameters.
- Use the Debug Tool Setup Utility (DTSU). DTSU helps you allocate all the files you need to start your debug session, and can start your program or submit your batch job. For more information about DTSU, refer to Chapter 15, “Starting Debug Tool from the Debug Tool Utilities,” on page 69.

To begin a debug session, ensure your program has been compiled with the TEST compiler option, and take the following steps:

1. Make sure that the Debug Tool SEQAMOD library is in the load module search path.

Note: High-level qualifiers and load library names are specific to your installation. Ask the person who installed Debug Tool the name of the data set. By default, the name of the data set ends in SEQAMOD. This data set might already be in the linklist or included in your TSO logon procedure, in which case you don’t need to do anything to access it.

If you are using DTSU to start Debug Tool, it does this step for you.

2. Allocate all other data sets containing files your program needs.
3. If you want a session log file, allocate one. This is a file that keeps a record of your debug session and can be used as a commands file during subsequent sessions. Do not allocate the session log file to a terminal. For example, do not use `ALLOC FI(INSPLOG) DA(*)`.
4. Start your program with the TEST run-time option, specifying the appropriate suboptions, or include a call to `CEETEST`, `PLITEST`, or `__ctest()` in the program’s source.

The following two example CLISTs show how you might allocate the Debug Tool load library data set (SEQAMOD) if it is not in the linklist or TSO logon procedure:

```
PROC 0 TEST
TSOLIB ACTIVATE DA('hlq.SEQAMOD')
END
```

and


```

PROC 0 TEST
TSOLIB DEACTIVATE
FREE FILE(SEQAMOD)
ALLOCATE DA('hlq.SEQAMOD') FILE(SEQAMOD) SHR REUSE
TSOLIB ACTIVATE FILE(SEQAMOD)
END

```

If you store either example CLIST in MYID.CLIST(DTSETUP), you can execute the CLIST by entering the following at the TSO READY prompt:

```
EXEC 'MYID.CLIST(DTSETUP)'
```

The CLIST will execute and the appropriate Debug Tool data set will be allocated.

After allocating all necessary program data sets, the command line is used to allocate the preferences file `setup.pref` and the session log file `session.log` as shown in the following example:

```

ALLOCATE FILE(insppref) DATASET(setup.pref) REUSE
ALLOCATE FILE(insplog) DATASET(session.log) REUSE
CALL 'USERID1.MYLIB(TSTSCRPT)' '/TEST'

```

No primary commands file is created. The TEST run-time option is entered from the command line during invocation of the COBOL program `tstscrpt`. Default run-time suboptions are assumed, as well as the Language Environment default run-time options for your installation.

The following CLIST fragment shows how to define Debug Tool-related files and start the C program `prog1` with the TEST run-time option:

```

ALLOC FI(inspsafe) DA(debug.save)           REUSE
ALLOC FI(insplog)  DA(debug.log)            REUSE
ALLOC FI(insppref) DA(debug.preferen)       REUSE

CALL 'MYID.MYQUAL.LOAD(PROG1)' +
     ' TRAP(ON) TEST(*,*,insppref)/'

```

Files include the session log file, `debug.log`; the preferences file, `debug.preferen`; and the settings file, `debug.save`, a Debug Tool file that saves Debug Tool settings for use in future debug sessions. Its Debug Tool-supplied default ddname is `inspsafe`. All necessary data sets must exist prior to Starting this CLIST.

Starting your program from a terminal that works only in line mode results in a line-mode session of Debug Tool. If you want to debug in line mode and you have a 3270-compatible terminal that is capable of sustaining a full-screen session, you must specify `SET SCREEN OFF`. You can specify this with the TEST run-time option by including the command in a preferences file, or by specifying it as a command string (for example, `TEST(*,*, "SET SCREEN OFF", insppref)`).

To start Debug Tool from a terminal other than the terminal currently controlling your TSO session, use the `VTAM_LU_id` parameter to specify the LU id of a VTAM terminal. The VTAM terminal you specify controls your debugging session as long as you remain in full-screen mode. If you enter line mode, control reverts to your TSO terminal until you re-enter full-screen mode using the `SET SCREEN ON` command.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Recording your debug session in a log file” on page 122

Chapter 17, “Starting Debug Tool from a program,” on page 79

Related references

z/OS Language Environment Programming Guide

Starting Debug Tool in batch mode

You have two choices to start Debug Tool in batch mode:

- You can follow the instructions outlined in this section. This includes modifying your JCL to include the appropriate Debug Tool data sets and TEST runtime options.
- Use the Debug Tool Setup Utility (DTSU). DTSU can generate JCL that includes the appropriate Debug Tool data sets and TEST runtime options, and can submit your batch job. For more information about DTSU, refer to Chapter 15, “Starting Debug Tool from the Debug Tool Utilities,” on page 69.

Before starting Debug Tool in batch mode, ensure that you have compiled your program with the TEST compiler option. Next, modify the JCL to run your batch program to include the appropriate Debug Tool data sets and to specify the TEST run-time option. Finally, run the modified JCL.

Sample JCL for a batch debug session for the COBOL program, EMPLRUN, is provided below. The job card and data set names need to be modified to suit your installation.

```
//DEBUGJCL JOB <appropriate JOB card information>
/* *****
/* JCL to run a batch Debug Tool session
/* Program EMPLRUN was previously compiled with the COBOL
/* compiler TEST option
/* *****
//STEP1 EXEC PGM=EMPLRUN,
// PARM='/TEST(,INSPIN,,)'
/*
/* Include the Debug Tool SEQAMOD data set
/*
//STEPLIB DD DISP=SHR,DSN=userid.TEST.LOAD
// DD DISP=SHR,DSN=hlq.SEQAMOD
/*
/* Specify a commands file with DDNAME matching the one
/* specified in the /TEST runtime option above
/* This example shows inline data but a data set could be
/* specified like: //INSPIN DD DISP=SHR,DSN=userid.TEST.INSPIN
/*
//INSPIN DD *
        STEP;
        AT *
        PERFORM
            QUERY LOCATION;
            GO;
        END-PERFORM;
        GO;
        QUIT;
/*
/*
/* Specify a log file for the debug session
/* Log file can be a data set with LRECL >= 42 and <= 256
/* For COBOL only, use LRECL <= 72 if you are planning to
/* use the log file as a commands file in subsequent Debug
/* Tool sessions. You can specify the log file like:
/* //INSPLOG DD DISP=SHR,DSN=userid.TEST.INSPLOG
/*
//INSPLOG DD SYSOUT=*,DCB=(LRECL=72,RECFM=FB,BLKSIZE=0)
//SYSPRINT DD SYSOUT=*
```

```
//SYSUDUMP DD DUMMY
//SYSOUT DD SYSOUT=*
/*
//
```

You can debug an MVS batch job in full-screen mode. Use the MFI option to specify the LU name of a VTAM terminal that interacts with Debug Tool. In the previous example, change the EXEC statement to specify the LU name of the VTAM terminal. For example:

```
//STEP1 EXEC PGM=EMPLRUN,
// PARM='/TEST(,INSPIN,,MFI%ABC00001:)'
```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Appendix D, “Notes on debugging in batch mode,” on page 333

Chapter 30, “Entering Debug Tool commands,” on page 203

Appendix E, “Notes on debugging in remote debug mode,” on page 335

Programs that start outside of Language Environment

The functions described in this section are available only if you purchase and install IBM Debug Tool Utilities and Advanced Functions, Version 5 Release 1 (5655-M19).

To debug an MVS batch or TSO program that has an initial program that does not run under the control of Language Environment, including OS/VS COBOL programs, use the Debug Tool program EQANMDBG to start Debug Tool.

If the initial program does run under the control of Language Environment and subsequent programs run outside the control of Language Environment, you can use the methods described in “Programs that start in Language Environment” on page 89 to debug all the programs.

To start Debug Tool by using EQANMDBG, do one of the following options:

- By using the Debug Tool Setup Utility (DTSU) option 3 to run the programs either under TSO or in MVS batch.
- By modifying the MVS JCL, TSO CLIST or REXX EXEC that you use to start your program, making the following changes:
 - Change the name of the program to be started to EQANMDBG.
 - Make one of the following updates:
 - Change the parameters by adding the name of the program to be debugged and any required Debug Tool run-time parameters
 - Add a EQANMDBG DD statement that provides the name of the program to be debugged and any required Debug Tool run-time parameters.
 - Change the parameters by adding the name of the program to be debugged, and add an EQANMDBG DD statement that provides any required Debug Tool run-time parameters
 - Verify that the Debug Tool SEQAMOD and SEQABMOD libraries are in the load module search path.

These updates are described in more detail in the following sections.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 15, “Starting Debug Tool from the Debug Tool Utilities,” on page 69

Passing parameters to EQANMDBG

When you modify your JCL, CLIST, or REXX EXEC to start EQANMDBG, you pass the following parameters to EQANMDBG:

- The name of the user program to be debugged (required)
- Any of the following run-time options (optional):
 - TEST to specify Debug Tool options such as data sets containing Debug Tool commands and preferences, whether a remote debug session or remote debug mode using a VTAM terminal is to be used, the address of the terminal, and so on.
 - NATLANG to specify the national language used to communicate with Debug Tool
 - COUNTRY to specify a country code for Debug Tool
 - TRAP to specify whether Debug Tool is to intercept abends.

You can specify these parameters in one of following ways:

- “Passing parameters to EQANMDBG by using only the PARM string”
- “Passing parameters to EQANMDBG using only the EQANMDBG DD statement” on page 94
- “Passing parameters to EQANMDBG using the PARM string and EQANMDBG DD statement” on page 94

Refer to the following sections for more information related to the material discussed in this section.


Related references

Debug Tool run-time options (*Debug Tool for z/OS Reference and Messages*)

Passing parameters to EQANMDBG by using only the PARM string

The easiest way to pass parameters to EQANMDBG is to modify the PARM string to contain the name of the program to be debugged, optionally followed by any of the Debug Tool run-time options and the parameters required by your program.

The syntax for this string is:



The following table compares how a sample JCL statement might look like after you modify the PARM string:

Original sample JCL	Modified sample JCL
//STEP1 EXEC PGM=MYPROG,PARM='ABC,X(12) ' ... //	//STEP1 EXEC PGM=EQANMDBG, // PARM='MYPROG,NATLANG(UEN)/ABC,X(12) ' ... //

Passing parameters to EQANMDBG using only the EQANMDBG DD statement

If the user parameter string that you are passing to your program is too long to add the necessary Debug Tool parameters to the PARM string, you can leave the PARM string unchanged and pass all required parameters to Debug Tool by using the EQANMDBG DD statement.

When you add an EQANMDBG DD statement to your JCL or allocate the EQANMDBG file in your TSO session, it can point to a data set with any RECFM (F, V, or U) and any LRECL. The data set must contain one or more lines. If it contains more than one line, all trailing blanks are removed from each line. However, each line is assumed to start in column 1 with any leading blanks considered to be part of the parameter data. Sequence numbers are not supported in this file.

The following table compares original JCL and modified JCL:

Original JCL	Modified JCL
//STEP1 EXEC PGM=MYPROG,PARM='ABC,X(12)' ... //	//STEP1 EXEC PGM=EQANMDBG, // PARM='ABC,X(12)' //EQANMDBG DD * MYPROG, TEST(ALL,INSPIN,,MFI:*), NATLANG(ENU) /* ... //

Passing parameters to EQANMDBG using the PARM string and EQANMDBG DD statement

With this method you can put the name of the user program to be debugged as part of the PARM string, and then specify all other Debug Tool run-time options by using the EQANMDBG DD statement.

This can be desirable if you need to pass the same run-time parameters to several programs, you have room in the PARM string to add the name of the program to be debugged, but you do not have room to add all of the run-time parameters to the PARM string.

When you use this method, you must do the following:

- Include an EQANMDBG DD statement that includes, at a minimum, an asterisk as the first positional parameter to indicate that the user-program name is to be taken from the PARM string.
- Modify the PARM string to include the user-program name followed by a slash at the beginning of the PARM string.

The following table compares original JCL and modified JCL:

Original JCL	Modified JCL
//STEP1 EXEC PGM=MYPROG,PARM='ABC,X(12)' ... //	//STEP1 EXEC PGM=EQANMDBG, // PARM='MYPROG/ABC,X(12)' //EQANMDBG DD * *,TEST(ALL,INSPIN,,MFI:*),NATLANG(ENU) /* ... //

Chapter 19. Starting Debug Tool under CICS

After you decide what level of testing you want to employ during your debug session, you can start your program using the proper TEST run-time option for your language. If you are using Debug Tool, this requires no special procedures, although there are certain considerations depending on the environment where you are debugging your program. Before you begin your session, make sure all Debug Tool and program libraries are available and that all necessary Debug Tool files, such as the session log file, the primary commands file, the preferences file, and any desired USE files are defined and created. If the program you want to debug is authorized, ensure that the Debug Tool load library SEQAMOD is authorized and placed in the MVS LNKST concatenation.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Choosing a debug mode”

Chapter 18, “Starting Debug Tool for batch or TSO programs,” on page 89

“Starting Debug Tool in batch mode” on page 91

Choosing a debug mode

To use Debug Tool under CICS, you need to ensure that all of the required installation and configuration steps for CICS Transaction Server, Language Environment, and Debug Tool have been completed. For more information, refer to the installation and customization guides for each product.

You can start Debug Tool in one of the following ways:

Single terminal mode

Debug Tool displays its screens on the same terminal as the application.

This can be set up using CADP, DTCN, CEETEST, pragma, or CEEUOPT(TEST).

Dual terminal mode

Debug Tool displays its screens on a different terminal than the one used by the application. This can be set up with CADP, DTCN or CEDF.

If you are using Debug Tool in a multiple-CICS region environment and sharing the EQADTCN2 temporary storage queue, set your profile to a debugging Display ID that is located in the same CICS region that the task you want to debug will run in.

Batch mode

Debug Tool does not have a terminal, but uses a commands file for input and writes output to the log. This can be set up using CADP, DTCN, CEETEST, pragma, or CEEUOPT(TEST).

Remote debug mode

Debug Tool works with a remote debugger to display results on a graphical user interface. This can be set up using CADP, DTCN, CEETEST, pragma, or CEEUOPT(TEST).

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 13, "Preparing a CICS program," on page 55
"Methods for starting Debug Tool under CICS"
"Starting Debug Tool by using DTCN" on page 97
"Starting Debug Tool by using CADP" on page 98
"Starting Debug Tool by using CEEUOPT" on page 98
"Starting Debug Tool by using compiler directives" on page 99
"Starting Debug Tool under CICS by using CEDF" on page 99
Chapter 40, "Debugging CICS programs," on page 283

Methods for starting Debug Tool under CICS

There are several different mechanisms available to start Debug Tool under CICS. Each mechanism has a different advantage and are listed below:

- DTCN which is a full-screen CICS transaction that allows you to dynamically modify any Language Environment TEST or NOTEST run-time option with which your application was originally link-edited. You can also use DTCN to modify other Language Environment run-time options that are not specific to Debug Tool. See Chapter 13, "Preparing a CICS program," on page 55 to learn how to set up profiles by using DTCN.
- CADP which is a CICS transaction that enables you to manage debugging profiles. This transaction is available with CICS Transaction Server for z/OS Version 2 Release 3. CADP has the following advantages over DTCN:
 - With CADP, multiple profiles with a single program name can be added from the same display device. There is no limit to the number of profiles supported. With DTCN, a single profile, with up to eight program ids, can be added from a single display device. In either case, the program names can be specified with wild cards.
 - CADP provides the same abilities as DTCN for managing debug profiles for Language Environment applications. CADP can also help manage debug profiles for Java applications, Enterprise Java Beans (EJBs), and CORBA stateless objects.
 - CADP profiles are persistent, and are kept in VSAM files. Persistence means that if the CADP profile was present before a CICS region is restarted, the CADP profile will be present after the CICS region is restarted. For DTCN profiles, if the CICS region that owns the temporary storage queue where the debugging profiles were defined is restarted, the DTCN profiles must be added again after the region is restarted.
 - CADP profiles can be shared across a CICSplex.
- Language Environment CEEUOPT module link-edited into your application, containing an appropriate TEST option, which tells Language Environment to start Debug Tool every time the application is run.

This mechanism can be useful during initial testing of new code when you will want to run Debug Tool frequently.

- A compiler directive within the application, such as `#pragma runopts(test)` (for C and C++) or `CALL CEETEST`.

These directives can be useful when you need to run multiple debug sessions for a piece of code that is deep inside a multiple enclave or multiple CU application. The application runs without Debug Tool until it encounters the directive, at which time Debug Tool is started at the precise point that you specify. With `CALL CEETEST`, you can even make the invocation of Debug Tool conditional, depending on variables that the application can test.

- CICS CEDF utility where you can start a debug session in Dual Terminal mode alongside CEDF, using a special option on the CEDF command.

This mechanism does not require you to change the application link-edit options or code, so it can be useful if you need to debug programs that have been compiled with the TEST option, but do not have invocation mechanisms built into them.

If your program uses several of these methods, the order of precedence is determined by Language Environment. For more information about the order of precedence for Language Environment run-time options, see *z/OS Language Environment Programming Guide*.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Starting Debug Tool by using CEEUOPT” on page 98

“Starting Debug Tool under CICS by using CEDF” on page 99

Related references

“Debug modes under CICS” on page 284

Starting Debug Tool by using DTCN

DTCN is a menu-driven tool that allows you to specify when to activate Debug Tool for CICS programs. You can do this by entering your debugging requirements into the DTCN panels from your CICS terminal. DTCN then saves these debugging requirements in its repository. When a CICS program starts, Debug Tool is started if the task environment matches a repository item.

DTCN profiles contain the identifiers (IDs) of CICS resources to debug. These resource IDs can be Terminal, Transaction, Program, or User.

To debug a PL/I or C/C++ CICS program by using DTCN to start Debug Tool, update the link-edit step to include the EQADCCXT member from the Debug Tool library *hlq.SEQAMOD* into the program’s main load module. If you are using CICS TS 2.3 and CADP, you do not need to include EQADCCXT.

When CICS programs are started, Debug Tool monitors the tasks to find a task that contains a combination of Terminal ID, Transaction ID, Program ID, and User ID that matches a repository profile item. Debug Tool selects the best matching profile (the one with the greatest number of resource IDs that match the active task). If two tasks have an equal number of matching resource IDs, the older debug profile is selected.

For example, consider the following two profile items:

- First, Item 1 is saved, specifying resource ID program PROG1
- Later, Item 2 is saved, specifying resource ID user ID USER1

When PROG1 is run by USER1, profile item 1 is used.

If this situation occurs, an error message is sent to the system console, suggesting that DTCN users should specify additional resource qualification. So, in the above case, each profile item should be set up with both user ID and program ID.

DTCN not only provides the capability to specify **what** to debug by specifying debug resource IDs, DTCN also provides the capability to specify **how** the debug session will run, for example, whether a mainframe (MFI) or workstation (VAD) debug session is desired.

When a DTCN profile is active for a full-screen mode debugging session, Debug Tool preserves in the profile most of the breakpoint information for that session. When the DTCN profile is deleted, the breakpoint information is deleted. After you save the profile in the repository, DTCN shows the saved TEST string in the display field **Repository String**. When you are satisfied with the saved profile, press PF3 to exit DTCN.

How to end your CICS debugging session

After you have finished debugging your program, use DTCN again to turn off your debug profile by pressing PF6 to delete your debug profile and then pressing PF3 to exit. You do not need to remove EQADCCXT from the load module; in fact, it's a good idea to leave it there for the next time you want to start Debug Tool.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 5, "Preparing a COBOL program," on page 25

Starting Debug Tool by using CADP

CADP is an interactive transaction supplied by CICS Transaction Server for z/OS Version 2 Release 3. CADP helps you maintain persistent debugging profiles. When you start the CICS Transaction Server for z/OS Version 2 Release 3 region and you set the DEBUGTOOL system initialization parameter to YES, Debug Tool uses the CADP profile repository instead of the DTCN profile repository to find a matching debugging profile.

DTCN: If you start the CICS region with DEBUGTOOL=NO, DTCN will be the method for defining profiles; those defined in CADP will not be used to start Debug Tool sessions. You can use the CEMT transaction to set DEBUGTOOL dynamically. See *CICS Supplied Transactions* for information about the CEMT utility transaction.

Before using CADP, verify that you have done all the preparation tasks described in Chapter 13, "Preparing a CICS program," on page 55 and in the CICS books.

The CICS books provide a thorough description of how to use CADP.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 13, "Preparing a CICS program," on page 55

Related references

CICS Supplied Transactions

Starting Debug Tool by using CEEUOPT

To request that Language Environment start Debug Tool every time the application is run, assemble a CEEUOPT module with an appropriate TEST run-time option. It is a good idea to link-edit the CEEUOPT module into a library and just add an INCLUDE LibraryDDname(CEEUOPT-MemberName) statement to the link-edit options when you link your application. Once the application program has been placed in the load library (and NEWCOPY'd if required), whenever it is run Debug Tool will be started.

Debug Tool runs in the mode defined in the TEST run-time option you supplied, normally Single Terminal mode, although you could provide a primary commands file and a log file and not use a terminal at all.

To start Debug Tool, simply run the application. Don't forget to remove the CEEUOPT containing your TEST run-time option when you have finished debugging your program.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 16, "Starting Debug Tool by using the TEST run-time option," on page 73

Starting Debug Tool by using compiler directives

When compile-directives are processed by your program, Debug Tool will be started in single terminal mode (this method supports only single terminal mode).

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Starting Debug Tool with CEETEST" on page 79

Starting Debug Tool under CICS by using CEDF

No specific preparation is required to use CEDF to start Debug Tool other than compiling the application with the appropriate compiler options and saving the source/listing.

CEDF has an ",I" option that starts Debug Tool. This option starts both EDF and Debug Tool in Dual Terminal mode. In Dual Terminal mode, EDF and Debug Tool screens are displayed on the terminal where you issue the CEDF command; application screens are displayed on the application terminal.

Note: You need to know the id of each terminal. One way to get this information is by using the CEOT transaction. The output will include Ter(xxxx), where xxxx is the terminal id.

To start Debug Tool, enter the CEDF transaction as follows:

```
CEDF xxxx,ON,I
```

where xxxx is the terminal on which you want to start the transaction to be debugged. This terminal is where the application is started. It performs 3270 application I/O, while a Debug Tool session is started at the terminal where CEDF is started.

CICS will return a message verifying the terminal id of the second terminal. Then, on the xxxx terminal, enter:

```
TRAN
```

where TRAN is the id for the transaction being debugged.

Once the command is entered, Debug Tool will be started for all Language Environment-enabled programs that are running on the terminal where Debug Tool is started. Debug Tool will continue to be active on this terminal, even if you turn off EDF.

For example, to begin a Debug Tool session using terminal T304 as the debugging terminal and T305 as the terminal where you want to run your application, start the CEDF transaction as follows on T304:

```
CEDF T305,ON,I
```

Then, on terminal T305, enter the name of the transaction you are debugging:

```
TRAN
```

When you run your application on T305, Debug Tool is started on T304. Terminal T305 displays only application output, that is, a specific CICS command to write to the screen.

Chapter 20. Starting a full-screen debug session

You can start Debug Tool by using the Language Environment TEST run-time option in one of the following ways:

- Using the Debug Tool Setup Utility (DTSU). DTSU helps you allocate files and can start your program. The methods listed below describe how you manually perform the same tasks.
- For TSO programs that start in Language Environment, start your program with the TEST run-time option as shown in the following examples:

- For C, C++, and PL/I:

```
CALL 'USERID1.MYLIB(MYPROG)' 'TEST/prog arg list'
```

- For COBOL:

```
CALL 'USERID1.MYLIB(MYPROG)' 'prog arg list/TEST'
```

If your system programmer has not installed Debug Tool in the standard load module search path, you need to include the Debug Tool SEQAMOD library in your load module search path.

Contact your systems programmer if you do not know the name of the Debug Tool library on your system.

To control Debug Tool from a separate terminal, specify the VTAM LU identifier of the separate terminal in the TEST parameter, as in the following example:

```
'TEST(,,,MFI%TCP00001:)/''
```

- For MVS batch programs that start in Language Environment, start your Language Environment program with the TEST run-time option specifying the VTAM LU identifier of a terminal, as in the following example

```
EXEC PGM=MYPROG,PARM='TEST(,,,MFI%TCP00001:)/''
```

If your system programmer has not installed Debug Tool in the standard load module search path, you need to include the Debug Tool SEQAMOD library in your load module search path.

- For MVS batch programs that do not start in Language Environment, including OS/VS COBOL programs, start the non-Language Environment Debug Tool (EQANMDBG), and pass your program name and the TEST run-time option. Specify the VTAM LU identifier of a terminal, as in the following example:

```
EXEC PGM=EQANMDBG,PARM='MYPROG,TEST(,,,MFI%TCP00001:)/''
```

If your system programmer has not installed Debug Tool in the standard load module search path, you need to include the Debug Tool SEQAMOD and SEQABMOD libraries in your load module search path.

- For CICS, make sure Debug Tool is installed in your CICS region. Enter DTCN or CADP (in CICS Transaction Server for z/OS Version 2 Release 3 and later) to start the Debug Tool control transaction. Enter the name of the transaction and program that you want to debug and any other criteria, such as terminal id or user id. If you are using DTCN, press PF4 to save the default debugging profile, then press PF3 to exit the DTCN transaction. You are now setup to start your transaction and begin a debugging session.

If you are using CADP to manage your debugging profiles, make sure that the DEBUGTOOL system initialization parameter is set to YES.

- For CICS transactions that run non-Language Environment assembler programs or OS/VS COBOL programs, verify with your system administrator that the Debug Tool CICS global user exits are installed and active. If exits are active and

the non-Language Environment assembler or OS/VS COBOL programs are defined in a DTCN or CADP debugging profile, Debug Tool will debug the non-Language Environment assembler or OS/VS COBOL programs. These programs must be the first program to run at a CICS Link Level (for example, at the start of a task or through a CICS LINK or XCTL request).

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 15, "Starting Debug Tool from the Debug Tool Utilities," on page 69

Chapter 8, "Preparing a C program," on page 37

Chapter 9, "Preparing a C++ program," on page 41

Chapter 5, "Preparing a COBOL program," on page 25

Chapter 7, "Preparing a PL/I program," on page 33

"Ending a full-screen debug session" on page 134

"Entering commands on the session panel" on page 114

"Passing parameters to EQANMDBG" on page 93

Related references

"Debug Tool session panel" on page 107

Chapter 21. Starting Debug Tool in other environments

You can start Debug Tool to debug batch programs in full-screen mode and from DB2 stored procedures.

Starting a debugging session in full-screen mode through a VTAM terminal

You can debug batch programs interactively by using a full-screen mode debugging session through a VTAM terminal. Before you start this debugging session, contact your system administrator to verify that your system was customized to support this type of debugging session.

To start a debugging session in full-screen mode through a VTAM terminal, do the following:

1. Start two terminal emulators. Connect the second terminal emulator to a terminal LU that can handle a full-screen mode debugging session through a VTAM terminal.
2. On the first terminal emulator, log on to TSO.
3. Note the LU name of the second terminal emulator. If the second terminal emulator displays a session manager screen, exit from the session manager.
4. Edit the PARM string of your batch job so that you specify the TEST run time parameter as follows:
`TEST(,,MFI%luname:*)`

Place a slash (/) before or after the parameter, depending on your programming language. *luname* is the VTAM LU name of the second terminal emulator.

5. Submit the batch job.
6. On the second emulator session, a full-screen mode debugging session is displayed. Interact with it in the same way you with any other full-screen mode debugging session.

After the debugging session has ended, repeat steps 5 and 6 to create another full-screen mode debugging session.

Starting Debug Tool from DB2 stored procedures: troubleshooting

The examples used in this section are based on examples introduced in Chapter 12, "Preparing a DB2 stored procedures program," on page 53.

If the remote debugger does not start when the stored procedure calls it, verify that the TCP/IP address is defined correctly in the DB2 catalog. When the stored procedure is called, the remote debugger source window is refreshed with the source or listing of the stored procedure.

To verify that the stored procedure has started, enter the following DB2 Display command, where *xxxx* is the name of the stored procedure:

```
Display Procedure(xxxx)
```

If the stored procedure is not started, enter the following DB2 command:

```
Start procedure(xxxx)
```

To switch from remote debug mode to full-screen mode through a VTAM terminal, change the definition of the stored procedure as follows, where TCP00095 is the VTAM LU name:

```
alter procedure SPROC1 run options 'TEST(,,MFI%TCP00095:).'
```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 4, “Planning your debug session and collecting resources,” on page 21

Part 4. Debugging your programs in full-screen mode

Chapter 22. Using full-screen mode: overview

The topics below describe the Debug Tool full-screen interface, and how to use this interface to perform common debugging tasks.

Debugging your programs in full-screen mode is the easiest way to learn how to use Debug Tool, even if you plan to use batch or line modes later.

Note: The PF key definitions used in these topics are the default settings.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 20, "Starting a full-screen debug session," on page 101

"Ending a full-screen debug session" on page 134

"Entering commands on the session panel" on page 114

"Navigating through Debug Tool session panel windows" on page 119

"Recording your debug session in a log file" on page 122

"Setting breakpoints to halt your program at a line" on page 124

"Stepping through or running your program" on page 124

"Displaying and monitoring the value of a variable" on page 127

"Displaying error numbers for messages in the Log window" on page 133

"Finding a renamed source, listing, or separate debug file" on page 133

"Requesting an attention interrupt during interactive sessions" on page 134

Chapter 26, "Debugging a C program in full-screen mode," on page 163

Chapter 27, "Debugging a C++ program in full-screen mode," on page 173

Chapter 23, "Debugging a COBOL program in full-screen mode," on page 137

Chapter 25, "Debugging a PL/I program in full-screen mode," on page 155

Debug Tool session panel

The Debug Tool session panel contains a header with information about the program you are debugging, a command line, and up to three windows.

Source window

Displays your program source code

Log window

Records your commands and Debug Tools responses

Monitor window

Continuously displays the value of monitored variables and other items, depending on the command used

The Debug Tool session panel below shows the default layout for the Monitor window **1**, the Source window **2**, and the Log window **3**.

```

COBOL    LOCATION: IBTUF4 :> 100.1
Command ==>
MONITOR --+---1---+---2---+---3---+---4---+---5---+---6 LINE: 1 OF 3
***** TOP OF MONITOR *****
0001 1 77 IBTUF4:>VARBL2 21
0002 2 77 IBTUF4:>VARBL1 11 1
0003 3 77 IBTUF4:>X 1
***** BOTTOM OF MONITOR *****
SOURCE: IBTUF4 --1---+---2---+---3---+---4---+---5--- LINE: 98 OF 118
    98      ADD 1 TO VARBL1 .
    99 2    ADD 1 TO VARBL2 .
   100      CALL "SUBPRO1" USING BY CONTENT PARAM1 .
   101      ADD 1 TO X .
   102      END-PERFORM. .
LOG 0--+---1---+---2---+---3---+---4---+---5---+--- LINE: 13 OF 19
0013 The command element MONITOR is invalid.
0014 MONITOR
0015 LIST VARBL2 ;
0016 MONITOR 3
0017 LIST VARBL1 ;
0018 MONITOR
0019 LIST X ;

```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Customizing the layout of windows on the session panel” on page 194

Related references

“Session panel header”

“Monitor window” on page 111

“Source window” on page 110

“Log window” on page 112

Session panel header

The first few lines of the Debug Tool session panel contain a command line and header fields that display information about the program that you are debugging.

Below is an example header for a C program.

```

C 1 LOCATION: MYID.SOURCE(TSTPGM1):>248 2
Command ==> 3 SCROLL ==> PAGE 4
5

```

Below is an example header for a COBOL program.

```

COBOL 1 LOCATION: XYZPROG.:>SUBR:>118 2
Command ==> 3 SCROLL ==> PAGE 4
5
:

```

The header fields are described below.

1 Assemble, C, COBOL, OS COBOL, Disassem, or PL/I

The name of the current programming language. This language is not necessarily the programming language of the code in the Source window. The language that is displayed in this field determines the syntax rules that you must follow for entering commands.

Notes:

1. Debug Tool does not differentiate between C and C++ programs. If there is a C++ program in the Source window, only C is displayed in this field.
2. OS COBOL is used to indicate OS/VS COBOL.

2 LOCATION

The program unit name and statement where execution is suspended, usually in the form *compile unit:>nnnnnn*.

In the C example above, execution in MYID.SOURCE(TSTPGM1) is suspended at line 248.

In the COBOL example above, execution in XYZPROG is suspended at XYZPROG::>SUBR:>118, or line 118 of subroutine SUBR.

If you are replaying recorded statements, the word "LOCATION" is replaced by PBK<LOC or PBK>LOC. The < and > symbols indicate whether the recorded statements are being replayed in the backward (<) or forward (>) direction.

If you are using the Enterprise PL/I compiler or the C/C++ compiler, the compile unit name is the entire data set name of the source. If the setting for LONGCUNAME is ON (the default) to display the CU name in long form, the name might be truncated.

3 COMMAND

The input area for the next Debug Tool command. You can enter any valid Debug Tool command here.

4 SCROLL

The number of lines or columns that you want to scroll when you enter a SCROLL command without an amount specified. To hide this field, enter the SET SCROLL DISPLAY OFF command. To modify the scroll amount, use the SET DEFAULT SCROLL command.

The value in this field is the operand applied to the SCROLL UP, SCROLL DOWN, SCROLL LEFT, and SCROLL RIGHT scrolling commands. Table 5 lists all the scrolling commands.

Table 5. Scrolling commands

Command	Description
<i>n</i>	Scroll by <i>n</i> number of lines.
HALF	Scroll by half a page.
PAGE	Scroll by a full page.
TOP	Scroll to the top of the data.
BOTTOM	Scroll to the bottom of the data.
MAX	Scroll to the limit of the data.
LEFT <i>x</i>	Scroll to the left by <i>x</i> number of characters.
RIGHT <i>x</i>	Scroll to the right by <i>x</i> number of characters.
CURSOR	Position of the cursor.
TO <i>x</i>	Scroll to line <i>x</i> , where <i>x</i> is an integer.

5 Message areas

Information and error messages are displayed in the space immediately below the command line.

Source window

```
1 SOURCE: MULTCU ---1-----2-----3-----4-----5---+ LINE: 70 OF 85
70      PROCEDURE DIVISION.
71      *****
72      * THIS IS THE MAIN PROGRAM AREA. This program only displays
73      *      text. 3
74      *****

2 75      DISPLAY "MULTCU COBOL SOURCE STARTED." UPON CONSOLE.
76      MOVE 25 TO PROGRAM-USHORT-BIN.
77      MOVE -25 TO PROGRAM-SSHORT-BIN. 4
78      PERFORM TEST-900.
79      PERFORM TEST-1000.
80      DISPLAY "MULTCU COBOL SOURCE ENDED." UPON CONSOLE.
```

The Source window displays the source file or listing. The Source window has four parts, described below.

1 Header area

Identifies the window, shows the compile unit name, and shows the current position in the source or listing.

2 Prefix area

Occupies the left-most eight columns of the Source window. Contains statement numbers or line numbers you can use when referring to the statements in your program. You can use the prefix area to set, display, and remove breakpoints with the prefix commands AT, CLEAR, ENABLE, DISABLE, QUERY, and SHOW.

3 Source display area

Shows the source code (for a C and C++ program), the source listing (for a COBOL or PL/I program), a pseudo assembler listing (for an assembler program), or the disassembly view (for programs without debug information) for the currently qualified program unit. If the current executable statement is in the source display area, it is highlighted.

4 Suffix area

A narrow, variable-width column at the right of the screen that Debug Tool uses to display frequency counts. It is only as wide as the largest count it must display.

The suffix area is optional. To show the suffix area, enter SET SUFFIX ON. To hide the suffix area, enter SET SUFFIX OFF. You can also set it on or off with the *Source Listing Suffix* field in the Profile Settings panel.

The labeled header line for each window contains a scale and a line counter. If you scroll a window horizontally, the scale also scrolls to indicate the columns displayed in the window. The line counter indicates the line number at the top of a window and the total number of lines in that window. If you scroll a window vertically, the line counter reflects the top line number currently displayed in that window.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using prefix commands on specific lines or statements” on page 116

“Customizing profile settings” on page 197

Monitor window

```
COBOL      LOCATION: MULTCU :> 75.1
Command ==>                               Scroll ==> PAGE
MONITOR --+---1---+---2---+---3---+---4---+---5---+---6 LINE: 1 OF 2
***** TOP OF MONITOR *****
0001  1 01 MULTCU:>PROGRAM-USHORT-BIN    00000
0002  2 01 MULTCU:>PROGRAM-SSHORT-BIN    +00000
***** BOTTOM OF MONITOR *****
```

Use the Monitor window to continuously display output from the MONITOR LIST, MONITOR QUERY, MONITOR DESCRIBE, and SET AUTOMONITOR commands. If this window is not open, Debug Tool opens it when you enter a MONITOR or SET AUTOMONITOR command. Its contents are refreshed whenever Debug Tool receives control and after every Debug Tool command that can affect the display.

When you issue a MONITOR command, it is assigned a reference number between 1 and 99, then added to the monitor list. You can specify the monitor number; however, you must either replace an existing monitor number or use the next sequential number.

When you issue the SET AUTOMONITOR ON command, the following line is displayed at the bottom of the list of monitored variables:

```
***** AUTOMONITOR *****
```

Variables that are added to the Monitor window as a result of the SET AUTOMONITOR command are displayed underneath this line.

While the MONITOR command can generate an unlimited amount of output, bounded only by your storage capacity, the Monitor window can display a maximum of only 1000 scrollable lines of output.

If a window is not wide enough to show all the output it contains, you can either issue SCROLL RIGHT (to scroll the window to the right) or ZOOM (to make it fill the screen).

The labeled header line for each window contains a scale and a line counter. If you scroll a window horizontally, the scale also scrolls to indicate the columns displayed in the window. The line counter indicates the line number at the top of a window and the total number of lines in that window. If you scroll a window vertically, the line counter reflects the top line number currently displayed in that window.

You can update the values of monitored variables by typing new values over the displayed values.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Displaying and monitoring the value of a variable” on page 127

“Scrolling the windows” on page 119

Log window

```
LOG 0-----1-----2-----3-----4-----5-----6 LINE: 6 OF 14
0007 MONITOR
0008 LIST PROGRAM-USHORT-BIN ;
0009 MONITOR
0010 LIST PROGRAM-SSHORT-BIN ;
0011 AT 75 ;
0012 AT 77 ;
0013 AT 79 ;
0014 GO ;
```

The Log window records and displays your interactions with Debug Tool.

At the beginning of a debug session, if you have specified any of the following files, the Log window displays messages indicating the beginning and end of any commands issued from these files:

- global preferences file
- preferences file (which is specified by using the TEST runtime option)
- commands file

If a global preferences file exists, the data set name of the global preferences file is displayed.

The following commands are not recorded in the Log window.

```
PANEL
FIND
CURSOR
RETRIEVE
SCROLL
WINDOW
IMMEDIATE
QUERY prefix command
SHOW prefix command
```

If SET INTERCEPT ON is in effect for a file, that file's output also appears in the Log window.

You can optionally exclude STEP and GO commands from the log by specifying SET ECHO OFF.

Commands that can be used with IMMEDIATE, such as the SCROLL and WINDOW commands, are excluded from the Log window.

By default, the Log window keeps 1000 lines for display. The default value can be changed by one of the following methods:

- The system administrator changes it through a global preferences file.
- You can change it through a preferences file.
- You can change it by entering SET LOG KEEP *n*, where *n* is the number of lines you want kept for display

The maximum number of lines is determined by the amount of storage available.

The labeled header line for each window contains a scale and a line counter. If you scroll a window horizontally, the scale also scrolls to indicate the columns displayed in the window. The line counter indicates the line number at the top of a

window and the total number of lines in that window. If you scroll a window vertically, the line counter reflects the top line number currently displayed in that window.

Creating a preferences file

If you have a preference as to the appearance or behavior of Debug Tool, you can set these options in a preferences file. You can modify the layout of the windows of the session panel, set PF keys to specific actions, or change the colors use in the session panel. “Saving customized settings in a preferences files” on page 199 describes what you can specify in a preferences file and how to make Debug Tool use your preferences file.

If your site has preferences for all users to use, the system administrator can set these preferences in a global preferences file. When Debug Tool starts, it does the following steps:

1. Checks for a global preferences file and runs any commands specified in the global preferences file.
2. If you specify a preference files, looks for that preferences file and runs any commands in that preferences file.
3. If you specify a commands file, looks for that commands file and runs any commands in that commands file.

Because of the order in which Debug Tool processes these files, any settings that you specify in your preferences and commands files can override settings in the global preferences file.

Displaying the source

Debug Tool displays your source in the Source Window using a source, listing, or separate debug file, depending on the compiler.

When you start Debug Tool, if your source is not displayed, press PF4. This puts you in the Source Identification panel. The Source Identification panel indicates the name of the source, listing or separate debug file that Debug Tool intended to use. With this name, you can verify if the file exists or if you have authorization to access it. If your file is stored at a different location, do one of the following:

- Use the SET SOURCE command with the new name of the source, listing, or debug file.
- Use the SET DEFAULT LISTINGS command with the new name of the source, listing or debug file (provided they are stored in a PDS).
- Type over the *Listing/Source file* field in the Source Identification panel with the new name for the source, listing, or separate debug file.
- Use the EQADEBUG DD statement to define the location of the file.
- Code the EQAUEDAT user exit with the location.

If there is no debug data, you can display the disassembled code by entering the SET DISASSEMBLY command.

To be able to view your COBOL source code while debugging in full-screen or remote debug mode, you must direct the source or listing to a non-temporary file that is available during the debug session. If you are debugging a Enterprise COBOL for z/OS and OS/390 or COBOL for OS/390 & VM program and specified the SEPARATE suboption of the compiler option, the listing does not need to be

saved, but the separate debug file must be a non-temporary file. The separate debug file must also be available during the debug session.

To be able to view your PL/I listing while debugging in full-screen or remote debug mode, PL/I for MVS™ & VM and OS PL/I programs must be compiled using the PL/I SOURCE compiler option. You must also direct the listing to a non-temporary file that is available during the debug session. During a debug session, Debug Tool displays the first file it finds named `userid.pgmname.list` in the Source window.

To be able to view your listing for Enterprise PL/I programs while debugging in full-screen or remote debug mode, you must direct the listing to a non-temporary file that is available during the debug session.

To be able to view your listing for C and C++ programs while debugging in full-screen or remote debug mode, you must direct the listing to a non-temporary file that is available during the debug session.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Appendix B, “How does Debug Tool locate debug information and source or listing files?,” on page 325

Debug Tool for z/OS Reference and Messages

Entering commands on the session panel

You can enter a command or modify what is on the session panel in seven areas, as shown below.

```
C          LOCATION: MYID.SOURCE(ICFSSCU1) ;> 89
Command ==> 1                               Scroll ==> PAGE 2
MONITOR --+---1---+---2---+---3---+---4---+---5---+---6 LINE: 1 OF 2
***** TOP OF MONITOR *****
0001 1 VARBL1 10
0002 2 VARBL2 20
***** BOTTOM OF MONITOR *****
SOURCE: ICFSSCU1 - 3 --+---2---+---3---+---4---+---5---+ LINE: 81 OF 96
81  main()
82  {
83      int VARBL1 = 10;
4  84      int VARBL2 = 20;
85      int R = 1;
86
87      printf("— IBFSSCC1 : BEGIN\n");
5
88      do {
89          VARBL1++;
90          printf("INSIDE PERFORM\n");
91          VARBL2 = VARBL2 - 2;
92          R++;
LOG 6 --+---1---+---2---+---3---+---4---+---5---+---6 LINE: 7 OF 15
0007 STEP ;
0008 AT 87 ;
0009 MONITOR
0010 LIST VARBL1 ;
0011 MONITOR
0012 LIST VARBL2 ;
0013 GO ;
7
0014 STEP ;
0015 STEP ;
```

1 Command line

You can enter any valid Debug Tool command on the command line.

2 Scroll area

You can redefine the default amount you want to scroll by typing the desired value over the value currently displayed.

3 Compile unit name area

You can change the qualification by typing the desired qualification over the value currently displayed. For example, to change the current qualification from ICFSSCU1, as shown in the Source window header, to ICFSSCU2, type ICFSSCU2 over ICFSSCU1 and press Enter.

4 Prefix area

You can enter only Debug Tool prefix commands in the prefix area, located in the left margin of the Source window.

5 Source window

You can modify any lines in the Source window and place them on the command line.

6 Window id area

You can change your window configuration by typing the name of the window you want to display over the name of the window that is currently being displayed.

7 Log window

You can modify any lines in the log and have Debug Tool place them on the command line.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using the session panel command line”

“Issuing system commands” on page 116

“Using prefix commands on specific lines or statements” on page 116

“Using commands that are sensitive to the cursor position” on page 117

“Using Program Function (PF) keys to enter commands” on page 117

“Retrieving previous commands” on page 118

“Retrieving commands from the Log and Source windows” on page 118

Related references

“Order in which Debug Tool accepts commands from the session panel”

“Initial PF key settings” on page 117

Order in which Debug Tool accepts commands from the session panel

If you enter commands in more than one valid input area on the session panel and press Enter, the input areas are processed in the following order of precedence.

1. Prefix area
2. Command line
3. Compile unit name area
4. Scroll area
5. Window id area
6. Source/Log window

Using the session panel command line

You can enter any Debug Tool command in the command field. You can also enter any TSO command by prefixing them with SYSTEM or TS0. Commands can be up to 48 SBCS characters or 23 DBCS characters in length.

If you need to enter a lengthy command, Debug Tool provides a command continuation character, the SBCS hyphen (-). When the current programming language is C and C++, you can also use the back slash (\) as a continuation character.

Debug Tool also provides automatic continuation if your command is not complete; for example, if the command was begun with a left brace ({) that has not been matched by a right brace (}). If you do need to continue your command, Debug Tool provides a MORE ==> prompt that is equivalent to another command line. You can continue to request additional command lines with continuation characters until you complete your command.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 30, “Entering Debug Tool commands,” on page 203

Issuing system commands

During your Debug Tool session, you can still access your base operating system using the SYSTEM command. The string following the SYSTEM command is passed on to your operating system. You can communicate with TSO in a TSO environment. For example, if you want to see a TSO catalog listing while in a debugging session, enter `SYSTEM LISTC;`.

When you are entering system commands, you must comply with the following:

- A command is required after the SYSTEM keyword. Do not enter any required parameters. Debug Tool prompts you.
- If you are debugging in batch and need system services, you can include commands and their requisite parameters in a CLIST and substitute the CLIST name in place of the command.
- If you want to enter several TSO commands, you can include them in a USE file, a procedure, or other commands list. Or you can enter:
`SYSTEM ISPF;`

This starts ISPF and displays an ISPF panel on your host emulator screen that you can use to issue commands.

For CICS only: The SYSTEM command is not supported.

TS0 is a synonym for the SYSTEM command. Truncation of the TS0 command is not allowed.

Using prefix commands on specific lines or statements

Certain commands, known as *prefix commands*, can be typed over the prefix area in the Source window, and then processed by pressing Enter. These commands (AT, CLEAR, DISABLE, ENABLE, QUERY, and SHOW) pertain only to the line or lines of code before which they are typed. For example, the AT command typed in the prefix area of a specific line sets a statement breakpoint only at that line.

You can use prefix commands to specify the particular verb or statement in the line where you want the command to apply. For example, AT typed in the prefix area of a line sets a statement breakpoint at the first relative statement in that line, while AT 3 sets a statement breakpoint at the third relative statement in that line. Typing DISABLE 3 in the prefix area and pressing Enter disables that breakpoint.

Using commands that are sensitive to the cursor position

Certain commands are sensitive to the position of the cursor. These commands, called *cursor-sensitive* commands, include all those that contain the keyword `CURSOR` (`AT CURSOR`, `DESCRIBE CURSOR`, `FIND CURSOR`, `LIST CURSOR`, `SCROLL...CURSOR`, `TRIGGER AT CURSOR`, `WINDOW...CURSOR`).

To enter a cursor-sensitive command, type it on the command line, position the cursor at the location in your Source window where you want the command to take effect (for example, at the beginning of a statement or at a verb), and press Enter.

You can also issue cursor-sensitive commands by assigning them to PF keys.

Note: Do not confuse cursor-sensitive commands with the `CURSOR` command, which returns the cursor to its last saved position.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Defining PF keys” on page 193

Using Program Function (PF) keys to enter commands

The cursor-sensitive commands, as well as other full-screen tasks, can be issued more quickly by assigning the commands to PF keys. You can issue the `WINDOW CLOSE`, `LIST`, `CURSOR`, `SCROLL TO`, `DESCRIBE ATTRIBUTES`, `RETRIEVE`, `FIND`, `WINDOW SIZE`, and the scrolling commands (`SCROLL UP`, `DOWN`, `LEFT`, and `RIGHT`) this way. Using PF keys makes tasks convenient and easy.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Defining PF keys” on page 193

“Using commands that are sensitive to the cursor position”

Related references

“Initial PF key settings”

Initial PF key settings

The table below shows the initial PF key settings.

PF key	Label	Definition	Use
PF1	?	?	“Getting online help for Debug Tool command syntax” on page 207
PF2	STEP	STEP	“Stepping through or running your program” on page 124
PF3	QUIT	QUIT	“Ending a full-screen debug session” on page 134
PF4	LIST	LIST	“Finding a renamed source, listing, or separate debug file” on page 133
PF4	LIST	LIST <i>variable_name</i>	“Displaying and monitoring the value of a variable” on page 127
PF5	FIND	IMMEDIATE FIND	“Finding a string in a window” on page 120

PF key	Label	Definition	Use
PF6	AT/CLEAR	AT TOGGLE CURSOR	"Setting breakpoints to halt your program at a line" on page 124
PF7	UP	IMMEDIATE UP	"Scrolling the windows" on page 119
PF8	DOWN	IMMEDIATE DOWN	"Scrolling the windows" on page 119
PF9	GO	GO	"Stepping through or running your program" on page 124
PF10	ZOOM	IMMEDIATE ZOOM	"Zooming a window to occupy the whole screen" on page 196
PF11	ZOOM LOG	IMMEDIATE ZOOM LOG	"Zooming a window to occupy the whole screen" on page 196
PF12	RETRIEVE	IMMEDIATE RETRIEVE	"Retrieving previous commands"

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Defining PF keys" on page 193

Retrieving previous commands

To retrieve the last command you entered, press PF12 (RETRIEVE). The retrieved command is displayed on the command line. You can make changes to the command, then press Enter to issue it.

To step backwards through previous commands, press PF12 to retrieve each command in sequence. If a retrieved command is too long to fit in the command line, only its last line is displayed.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Retrieving commands from the Log and Source windows"

Retrieving commands from the Log and Source windows

You can retrieve lines from the Log and Source windows and use them as new commands.

To retrieve a line, move the cursor to the desired line, modify it (for example, delete any comment characters) and press Enter. The input line appears on the command line. You can further modify the command, then press Enter to issue it.

When retrieving long or multiple Debug Tool commands, a pop-up window is displayed, with the command as typed in so far. However, trailing blanks on the last line are removed. To expand the pop-up window, place the cursor below it and press Enter.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Retrieving previous commands"

Navigating through Debug Tool session panel windows

You can navigate in any of the windows using the `CURSOR` command and the scrolling commands: `SCROLL UP`, `DOWN`, `LEFT`, `RIGHT`, `TO`, `NEXT`, `TOP`, and `BOTTOM`. You can also search for character strings using the `FIND` command, which scrolls you automatically to the specified string.

The window acted upon by any of these commands is determined by one of several factors. If you specify a window name (`LOG`, `MONITOR`, or `SOURCE`) when entering the command, that window is acted upon. If the command is cursor-oriented, the window containing the cursor is acted upon. If you do not specify a window name and the cursor is not in any of the windows, the window acted upon is determined by the settings of **Default window** and *Default scroll amount* under the Profile Settings panel.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Moving the cursor between windows”

“Scrolling the windows”

“Scrolling to a particular line number” on page 120

“Finding a string in a window” on page 120

“Changing which source file appears in the Source window” on page 120

“Displaying the line at which execution halted” on page 121

“Customizing profile settings” on page 197

Moving the cursor between windows

To move the cursor back and forth quickly from the Monitor, Source, or Log window to the command line, use the `CURSOR` command. This command, and several other cursor-oriented commands, are highly effective when assigned to PF keys. After assigning the `CURSOR` command to a PF key, move the cursor by pressing that PF key. If the cursor is not on the command line when you issue the `CURSOR` command, it goes there. To return it to its previous position, press the `CURSOR` PF key again.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Defining PF keys” on page 193

Scrolling the windows

If the cursor is on the command line, you can scroll the Source window by pressing PF7 (UP) or PF8 (DOWN). To scroll through other windows, place the cursor in the desired window before pressing PF7 or PF8.

You can toggle one of the Source, Log or Monitor windows to full screen (temporarily not displaying the others) by moving the cursor into the window you want to zoom and pressing PF10 (ZOOM). To toggle back, press PF10 again. PF11 (ZOOM LOG) toggles the Log window the same way without the cursor needing to be in the Log window.

You can scroll any of the windows vertically and horizontally by issuing the `SCROLL UP`, `DOWN`, `LEFT`, and `RIGHT` commands (the `SCROLL` keyword is optional). You can use the command line to specify which window to scroll. For example, to scroll the monitor window up 5 lines, enter `SCROLL UP 5 MONITOR`.

Alternately, you can use the position of the cursor to indicate the window you want to scroll; if the cursor is in a window, that window is scrolled. If you do not specify the window, the default window (determined by the setting of the `DEFAULT WINDOW` command) is scrolled. You can change the default window by changing the settings of **Default window** and *Default scroll amount* under the Profile Settings panel.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Customizing the layout of windows on the session panel” on page 194

“Scrolling to a particular line number”

“Customizing profile settings” on page 197

Scrolling to a particular line number

To display a particular line at the top of a window, use the `SCROLL TO` command with the statement numbers shown in the window prefix areas. Enter `SCROLL TO n` (where *n* is a line number) on the command line and press Enter.

For example, to bring line 345 to the top of the window, enter `SCROLL TO 345` on the command line. The selected window is scrolled vertically so that your specified line is displayed at the top of that window.

Finding a string in a window

To find the next occurrence of a string within a window:

1. On the command line, type the string you want to find, enclosed in double quotes (assembler, C, C++, COBOL, or disassembly) or single quotes (assembler, disassembly, or PL/I), but **do not** press Enter.
2. Move the cursor into the window to be searched.
3. Press PF5 (FIND).

To repeat the search in whatever window the cursor is in, press PF5 again.

Changing which source file appears in the Source window

To change which source file appears in the Source window, type over the name after `SOURCE:`, which is in the Header area of the Source window, with the desired name. The new name must be the name of a compile unit (CU) that is known to Debug Tool. To determine which CUs are known to Debug Tool, enter the `LIST NAMES CUS` command. By default, the `LIST NAMES CUS` command does not display the names of disassembled CUs. If you are debugging an assembler or disassembly program and want the `LIST NAMES CUS` to display the names of the disassembled CUs, enter the `SET DISASSEMBLY ON` or `SET ASSEMBLER ON` command before you enter the `LIST NAMES CUS` command.

Alternately, you can enter the command:

```
LIST NAMES CUS
```

and a list of compile units will be written to the Log window, as shown below.

```
USERID.MFISTART.C(CALC)
USERID.MFISTART.C(PUSHPOP)
USERID.MFISTART.C(READTKN)
```

You can type over or insert characters on one of these lines in the Log window and press Enter to display the modified text on the command line, for example:


```
SET QUALIFY CU "USERID.MFISTART.C(READTKN)"
```

and then press Enter to issue the command. Typing over a line in the Log window and issuing them as commands is a way to save keystrokes and reduce errors in long commands.

Another way to change which source file appears in the Source window is to press PF4 (LIST) with the cursor on the command line. This displays the Source Identification Panel, where associations are made between listings or source files shown in the Source window and their compile units. Type over the *Listings/Source File* field with the new name.

For C and C++ only

For C and C++ compile units, Debug Tool requires a file containing the source code. By default, when Debug Tool encounters a new C and C++ compile unit, it looks for the source code in a file whose name is the one that was used in the compile step.

For COBOL and PL/I only

For COBOL and PL/I compile units, Debug Tool requires a file containing the compiler listing. By default, when Debug Tool encounters a new VS COBOL II or a non-Enterprise PL/I compile unit, it looks for the listing in a file named `userid.cuname.LIST`. For Enterprise PL/I, Debug Tool looks for the listing in the data set specified in the load module. For COBOL/370™ and COBOL for MVS & VM, Debug Tool looks for the listing in the data set specified during the compile step. For Enterprise COBOL for z/OS and OS/390 and COBOL for OS/390 & VM, there are two possible places Debug Tool looks for compiler listing:

- Debug Tool look for the listing in the data set specified during the compile step.
- If your program is compiled with the SEPARATE suboption of the TEST compiler option, Debug Tool looks for the compiler listing in the separate debug file.
- **Related tasks**
- “Finding a renamed source, listing, or separate debug file” on page 133

Displaying the line at which execution halted

After displaying different source files and scrolling, you can go back to the halted execution point by entering one of the following commands:

- SET QUALIFY RESET
- Q LOC
- LIST %LINE

Creating a commands file

A commands file is a convenient method of reproducing debug sessions or resuming interrupted sessions. Use one of the following methods to create a commands file:

- Record your debug session in a log file and then use the log file as a commands file. This is the fastest way to create a valid commands file.
- Create a commands file manually.

For PL/I programs, if your commands file has sequence numbers in columns 73 through 80, you must enter the SET SEQUENCE ON command as the first command in the commands file or before you use the commands file. After you enter this command, Debug Tool does not interpret the data in columns 73 through 80 as a

command. Later, if you want Debug Tool to interpret the data in columns 73 through 80 as a command, enter the command SET SEQUENCE OFF.

Recording your debug session in a log file

Debug Tool can record your commands and their generated output in a session log file. This allows you to record your session and use the file as a reference to help you analyze your session strategy. You can also use the log file as a command input file in a later session by specifying it as your primary commands file. This is a convenient method of reproducing debug sessions or resuming interrupted sessions.

The following appear as comments (preceded by an asterisk {*} in column 7 for COBOL programs, and enclosed in /* */ for C and C++ or PL/I programs):

- All command output
- Commands from USE files
- Commands specified on a __ctest() function call
- Commands specified on a CALL CEETEST statement
- Commands specified on a CALL PLITEST statement
- Commands specified in the run-time TEST command string suboption
- QUIT commands
- Debug Tool messages about the program execution (intercepted console messages, exceptions, etc.)

The default ddname associated with the Debug Tool session log file is INSPLOG. If you do not allocate a file with ddname INSPLOG, no default log file is created.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Creating the log file”

“Recording how many times each source line runs” on page 123

Creating the log file

To create a permanent log of your debug session, first create a file with the following specifications:

- A logical record length between 32 and 256. If the log file has a logical record length outside the limits, Debug Tool issues a message and does not use the file.
- The record format and block size have no restrictions.

Then, allocate the file to the DD name INSPLOG in the CLIST, JCL, or EXEC you use to run your program.

For COBOL only, if you want to subsequently use the session log file as a commands file, make the LRECL less than or equal to 72. Debug Tool ignores everything after column 72 for file input during a COBOL debug session.

For CICS only, SET LOG OFF is the default. To start the log, you must use the SET LOG ON file command. For example, to have the log written to a data set named TSTPINE.DT.LOG , issue: SET LOG ON FILE TSTPINE.DT.LOG;

Make sure the default of SET LOG ON is still in effect. If you have issued SET LOG OFF, output to the log file is suppressed. If Debug Tool is never given control, the log file is not used.

When the default log file (INSPLOG) is accessed during initialization, any existing file with the same name is overwritten. On MVS, if the log file is allocated with disposition of MOD, the log output is appended to the existing file. Entering the SET LOG ON FILE xxx command also appends the log output to the existing file.

If a log file was not allocated for your session, you can allocate one with the SET LOG command by entering:

```
SET LOG ON FILE logddn;
```

This causes Debug Tool to write the log to the file which is allocated to the DD name LOGDDN.

Note: A sequential file is recommended for a session log since Debug Tool writes to the log file.

At any time during your session, you can stop information from being sent to a log file by entering:

```
SET LOG OFF;
```

To resume use of the log file, enter:

```
SET LOG ON;
```

The log file is active for the entire Debug Tool session.

Debug Tool keeps a log file in the following modes of operation: line mode, full-screen mode, and batch mode.

Recording how many times each source line runs

To record of how many times each line of your code was executed:

1. Allocate the INSPLOG file if you want to keep a permanent record of the results.
2. Issue the command:

```
SET FREQUENCY ON;
```

After you have entered the SET FREQUENCY ON command, your Source window is updated to show the current frequency count. Remember that this command starts the statistic gathering to display the actual count, so if your application has already executed a section of code, the data for these executed statements will not be available.

If you want statement counts for the entire program, issue:

```
GO ;  
LIST FREQUENCY * ;
```

which lists the number of times each statement is run. When you quit, the results are written to the Log file. You can issue the LIST FREQUENCY * at any time, but it will only display the frequency count for the currently active compile unit.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Creating the log file” on page 122

Recording the breakpoints encountered

If you are debugging a compile unit that does not support automonitoring, you can use the SET AUTOMONITOR command to record the breakpoints encountered in that compile unit. After you enter the SET AUTOMONITOR ON command, Debug Tool records the location of each breakpoint that is encountered, as if you entered the QUERY LOCATION command.

Setting breakpoints to halt your program at a line

To set or clear a line breakpoint, move the cursor over an executable line in the Source window and press PF6 (AT/CLEAR). You can temporarily turn off the breakpoint with DISABLE and turn it back on with ENABLE.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Halting on a line in C only if a condition is true” on page 167

“Halting on a line in C++ only if a condition is true” on page 178

“Halting on a COBOL line only if a condition is true” on page 142

“Halting on a PL/I line only if a condition is true” on page 159

Stepping through or running your program

By default, when Debug Tool starts, none of your program has run yet (including C++ constructors and static object initialization).

To run your program up to the next hook, press PF2 (STEP). If you compiled with TEST for C or C++, TEST(ALL,SYM) for COBOL or PL/I, or TEST(NONE,SYM) for Enterprise COBOL for z/OS and OS/390 or COBOL for OS/390 & VM with the Dynamic Debug facility activated, STEP performs one statement.

To run your program until a breakpoint is reached, the program ends, or a condition is raised, press PF9 (G0).

Note: A condition being raised is determined by the setting of the TEST run-time suboption *test_level*.

The command STEP OVER runs the called function without stepping into it. If you accidentally step into a function when you meant to step over it, issue the STEP RETURN command that steps to the return point (just after the call point).

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 4, “Planning your debug session and collecting resources,” on page 21
Chapter 16, “Starting Debug Tool by using the TEST run-time option,” on page 73

Recording and replaying statements

The commands described in this section are available only if you purchase and install IBM Debug Tool Utilities and Advanced Functions, Version 5 Release 1 (5655-M19).

Debug Tool provides a set of commands (the PLAYBACK commands) that helps you record and replay the statements that you run while you debug your program. To record and replay statements, you need to do the following:

1. Record the statements that you run (PLAYBACK ENABLE command). If you specify the DATA parameter or the DATA parameter is defaulted, additional information about your program is recorded.
2. Prepare to replay statements (PLAYBACK START command).
3. Replay the statements that you recorded (STEP or RUNTO command).
4. Change the direction that the statements are replayed (PLAYBACK FORWARD command).
5. Stop replaying statements (PLAYBACK STOP command).
6. Stop recording the statements that you run (PLAYBACK DISABLE command). All data for the compile units specified or implied on the PLAYBACK DISABLE command is discarded.

Each of these steps are described in more detail in the sections that follow.

Recording the statements that you run

The PLAYBACK ENABLE command includes a set of parameters to specify:

- Which compile units to record
- The maximum amount of storage to use to record the statements that you run
- Whether to record the following additional information about your program:
 - The value of variables.
 - The value of registers.
 - Information about the files you use: open, close, last operation performed on the files, how the files were opened.

The PLAYBACK ENABLE command can be used to record the statements that you run for all compile units or for specific compile units. For example, you can record the statements that you run for compile units A, B, and C, where A, B, and C are existing compile units. Later, you can enter the PLAYBACK ENABLE command and specify that you want to record the statements that you run for all compile units. You can use an asterisk (*) to specify all current and future compile units.

The number of statements that Debug Tool can record depends on the following:

- The amount of storage specified or defaulted.
- The number of changes made to the variables.
- The number of changes made to files.

You cannot change the storage value after you have started recording. The more storage that you specify, the more statements that Debug Tool can record. After Debug Tool has filled all the available storage, Debug Tool puts information about the most recent statements over the oldest information. When the DATA parameter is in effect, the available storage fills more quickly.

You can use the DATA parameter with programs compiled with the SYM suboption of the TEST compiler option only if they are compiled with the following compilers and are running with the following Language Environment run time and APARs installed:

- Compilers:
 - Enterprise COBOL for z/OS and OS/390, Version 3 Release 2

- Enterprise COBOL for z/OS and OS/390, Version 3 Release 1 with APAR PQ63235
- COBOL for OS/390 & VM, Version 2 with APAR PQ63234
- Language Environment APARs:
 - z/OS Version 1 Release 4, with APAR PQ65176
 - z/OS, Version 1 Release 3, with APAR PQ65175
 - z/OS, Version 1 Release 2, with APAR PQ65174 and APAR PQ52626
 - z/OS, Version 1 Release 1, with APAR PQ62947 and APAR PQ52626
 - OS/390, Version 2 Release 10, with APAR PQ62947 and APAR PQ52626

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Stop the recording”

Preparing to replay the statements that you recorded

The `PLAYBACK START` command notifies Debug Tool that you want to replay the statements that you recorded. This command suspends normal debugging; all breakpoints are suspended and you cannot use many Debug Tool commands. *Debug Tool for z/OS Reference and Messages* provides a complete list of which commands you cannot use while you replay statements.

The initial direction is backward.

Replaying the statements that you recorded

To replay the statements that you recorded, enter the `STEP` or `RUNTO` command. You can replay the statements you recorded until one of the following conditions is reached:

- If you are replaying in the backward direction, you reach the point where you entered the `PLAYBACK ENABLE` command. If you are replaying in the forward direction, you reach the point where you entered the `PLAYBACK START` command.
- You reach the point where there are no more statements to replay, because you have run out of storage.

You can replay as far forward as the point where you entered the `PLAYBACK START` command. As you replay statements, you see only the statements that you recorded for those compile units you indicated you wanted to record. While you are replaying steps, you cannot modify variables. If the `DATA` parameter is in effect, you can access the contents of variables and expressions.

Changing the direction that statements are replayed

To change the direction that statements are replayed, enter the `PLAYBACK FOWARD` or `PLAYBACK BACKWARD` command. The initial direction is backward.

Stop the replaying

To stop replaying the statements that you recorded and resume normal debugging, enter the `PLAYBACK STOP` command. This command resumes normal debugging at the point where you entered the `PLAYBACK START` command. Debug Tool continues to record the statements that you run.

Stop the recording

To stop recording the statements that you run and collecting additional information about your program, enter the `PLAYBACK DISABLE` command. This command can be

used to stop recording the statements that you run in all or specific compile units. If you stop recording for one or more compile units, the data collected for those compile units is discarded. If you stop recording for all compile units, the PLAYBACK START command is no longer available.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Restrictions on recording and replaying statements

You cannot modify the value of variables or storage while you are replaying statements.

When you replay statements, many Debug Tool commands are unavailable. *Debug Tool for z/OS Reference and Messages* contains a complete list of all the commands that are not available.

Restrictions on accessing COBOL data

If the DATA parameter is specified or defaulted for a COBOL compile unit that supports this parameter, you can access data defined in the following section of the DATA DIVISION:

- FILE SECTION
- WORKING-STORAGE SECTION
- LOCAL-STORAGE SECTION
- LINKAGE SECTION

You can also access special registers, except for the ADDRESS OF, LENGTH OF, and WHEN-COMPILED special registers. You can also access all the special registers supported by Debug Tool commands.

When you are replaying statements, many Debug Tool commands are available only if the following conditions are met:

- The DATA parameter must be specified or defaulted for the compile unit.
- The compile unit must be compiled with a compiler that supports the DATA parameter.

You can use the QUERY PLAYBACK command to determine the compile units for which the DATA option is in effect.

Debug Tool for z/OS Reference and Messages contains a complete list of all the commands that can be used when you specify the DATA parameter.

Displaying and monitoring the value of a variable

Debug Tool can display the value of variables in the following ways:

- One-time display, by using the LIST command or the PF4 key. One-time display displays the value of the variable at the moment you enter the LIST command or press the PF4 key. If you step or run through your program, any changes to the value of the variable are not displayed.
- Continuous display, called monitoring, by using the MONITOR LIST command or the SET AUTOMONITOR command. If you step or run through your program, any changes to the value of the variable are displayed.

If Debug Tool cannot display the value of a variable in its declared data type, Debug Tool displays the value of the variable in hexadecimal format. To change the value of the variable, type in the new value in hexadecimal format.

One-time display of the value of variables

To display the contents of a variable once by using the PF4 key, do the following steps:

1. Scroll through the Source window until you find the variable you want to display.
2. Move your cursor to the variable name.
3. Press the PF4 (LIST) key. The value of the variable is displayed in the Log window.

To display the contents of a variable once by using the LIST command, do the following step:

1. Move the cursor to the command line.
2. Type the following command, substituting your variable name for *variable-name*:
`LIST variable-name;`
3. Press Enter. The value of the variable is displayed in the Log window.

Monitoring the value of variables

To monitor the value of a variable by using the MONITOR LIST command, do the following steps:

1. Move the cursor to the command line.
2. Type the following command, substituting your variable name for *variable-name*:
`MONITOR LIST variable-name;`
3. Press Enter. The variable *variable-name* is added to the Monitor window and the current value of *variable-name* is displayed. As you step through your program, the value of *variable-name* is updated in the Monitor window so that the window always displays the current value of *variable-name*.

To monitor the value of a variable by using the SET AUTOMONITOR ON command, do the following steps:

1. Move the cursor to the command line.
2. Enter the following command:
`SET AUTOMONITOR ON;`

Debug Tool opens a separate section of the Monitor window, called the automonitor section, and displays the name and value of variables in the next statement that you run. Each time you enter the STEP command or a breakpoint is encountered, Debug Tool does the following:

- a. Removes the previous names and values.
- b. Displays the names and values of the variables of the statement that Debug Tool runs next. The values displayed are values *before* the statement is run.

To save the following information in the log file, enter the SET AUTOMONITOR ON LOG command:

- Breakpoint locations
- The names and values of the variables at the breakpoints

The default option is NOLOG, which would not save the above information.

Each entry in the log file contains the breakpoint location within the program and the names and values of the variables in the statement. To stop saving this information in the log file and continue updating the automonitor section of the Monitor window, enter the SET AUTOMONITOR ON NOLOG command.

Variables that are monitored through the MONITOR LIST command are displayed above the automonitor section of the Monitor window.

To close the automonitor section of the Monitor window and stop adding the name and value of variables in the statements your run, enter the SET AUTOMONITOR OFF command.

The SET AUTOMONITOR command is available only if you purchase and install IBM Debug Tool Utilities and Advanced Functions, Version 5 Release 1 (5655-M19).

Example: SET AUTOMONITOR ON command

The example in this section assumes that the following two lines of COBOL code are to be run:

```
COMPUTE LOAN-AMOUNT = FUNCTION NUMVAL(LOAN-AMOUNT-IN). 1  
COMPUTE INTEREST-RATE = FUNCTION NUMVAL(INTEREST-RATE-IN).
```

Before you run the statement in Line **1**, enter the following command:
SET AUTOMONITOR ON ;

The name and value of the variables LOAN-AMOUNT and LOAN-AMOUNT-IN are displayed in the automonitor section of the Monitor window. These values are the values of the variables before you run the statement.

Enter the STEP command. Debug Tool removes LOAN-AMOUNT and LOAN-AMOUNT-IN from the automonitor section of the Monitor window and then displays the name and value of the variables INTEREST-RATE and INTEREST-RATE-IN. These values are the values of the variables before you run the statement.

Displaying values in hexadecimal format

You can display the value of a variable in hexadecimal format by entering the LIST %HEX command or defining a PF key with the LIST %HEX command. For PL/I programs, to display the value of a variable in hexadecimal format, use the PL/I built-in function HEX. For more information about the PL/I HEX built-in function, see *VisualAge PL/I for OS/390 Programming Guide*. If you display a PL/I variable in hexadecimal format, you cannot edit the value of the variable by typing over the existing value in the Monitor window.

To display the value of a variable in hexadecimal format, enter one of the following commands, substituting *variable-name* with the name of your variable:

- For PL/I programs: LIST HEX(*variable-name*) ;
- For all other programs: LIST %HEX(*variable-name*) ;

Debug Tool displays the value of the variable *variable-name* in hexadecimal format.

If you defined a PF key with the LIST %HEX command, do the following steps:

1. If the variable is not displayed in the Source window, scroll through your program until the variable you want is displayed in the Source window.
2. Move your cursor to the variable name.

3. Press the PF key to which you defined LIST %HEX command. Debug Tool displays the value of the variable *variable-name* in hexadecimal format.

You cannot define a PF key with the PL/I HEX built-in function.

Monitoring the value of variables in hexadecimal format

You can monitor the value of a variable in either the variable's declared data type or in hexadecimal format. To monitor the value of a variable in its declared data type, follow the instructions described in "Monitoring the value of variables" on page 128. For PL/I programs, use the PL/I HEX built-in function to monitor the value of a variable in hexadecimal format. If you monitor a PL/I variable in hexadecimal format, you cannot edit the value of the variable by typing over the existing value in the Monitor window.

To monitor the value of a variable or expression in hexadecimal format, do one of the following instructions:

- If the variable is already being monitored, enter the following command:
MONITOR *n* HEX ;

Substitute *n* with the number in the monitor list that corresponds to the monitored expression that you would like to display in hex.

- If the variable is not being monitored, enter the following command:
MONITOR LIST (*expression*) HEX ;

Substitute *expression* with the name of the variable or a complex expression you want to monitor.

Modifying variables

There are two methods to modify variables:

- By using a command, such as MOVE or an assignment command. Each command is described in *Debug Tool for z/OS Reference and Messages*.
- By typing over the existing value that is displayed in the Monitor window.

To modify the value of a variable by typing over the existing value in the Monitor window, do the following steps:

1. Move the cursor to the existing value.
2. Type in the new value. Black vertical bars mark the area where you can type in your new value; you cannot type anything before and including the left vertical bar nor can you type anything including and after the right vertical bar.
3. Press Enter. Debug Tool creates a command in the command line that will do the modification.
4. Verify that the command that Debug Tool created is correct. Press Enter.

Restrictions for modifying variables in the Monitor window

You cannot remove variables in the automonitor section of the Monitor window by using the CLEAR command.

You can modify the value of a variable by typing over the existing value in the Monitor window, with the following exceptions:

- Only one value at a time can be modified. If you type over the values of more than one variable, only the first one is modified.

- You cannot type in a value that is larger than the declared type of the variable. For example, if you declare a variable as a string of four character and you try to type in five characters, Debug Tool prevents you from typing in the fifth character.
- If Debug Tool cannot display the entire value in the Monitor window, you cannot modify the value of that variable. If the variable is a structure and you want to modify an element of that structure, the element must not have an ambiguous name. An ambiguous name is a reference to an element that might have more than one definition. For example, if you have two structures in a C program and each structure has an element defined as `street_address char[15]`, the Monitor window must display the beginning of the structure so that Debug Tool can determine to which structure a specific element belongs to.
- If you enter quotes, carefully verify the command that Debug Tool creates to ensure that the command complies with any applicable quotation rules.

Opening and closing the Monitor window

If the Monitor window is closed before you enter the `SET AUTOMONITOR ON` command, Debug Tool opens the Monitor window and displays the name and value of the variables of statement you run in the automonitor section of the window.

If the Monitor window is open before you enter the `SET AUTOMONITOR OFF` command and you are watching the value of variables not monitored by `SET AUTOMONITOR ON`, the Monitor window remains open.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Displaying values of COBOL variables” on page 213

“Displaying values of C and C++ variables or expressions” on page 238

“Accessing PL/I program variables” on page 231

“Displaying and modifying the value of assembler variables or storage” on page 190

Managing file allocations

You can manage files while you are debugging by using the `DESCRIBE ALLOCATIONS`, `ALLOCATE`, and `FREE` commands. You cannot manage files while debugging CICS programs. These commands are available only if you purchase and install IBM Debug Tool Utilities and Advanced Functions, Version 5 Release 1 (5655-M19).

To view a current list of allocated files, enter the `DESCRIBE ALLOCATIONS` command. The following screen displays the command and sample output:

```

DESCRIBE ALLOCATIONS ;
* Current allocations:
* VOLUME CAT DISP OPEN DDNAME DSNAME
* 1 --- 2 - 3 ----- 4 - 5 ----- 6 -----
* COD008 * SHR KEEP * EQAZSTEP BCARTER.TEST.LOAD
* SMS004 * SHR KEEP SHARE.CEE210.SCEERUN
* COD00B * OLD KEEP * INSPLOG BCARTER.DTOOL.LOGV
* VIO NEW DELETE ISPCTL0 SYS02190.T085429.RA000.BCARTER.R0100269
* COD016 * SHR KEEP ISPEXEC BCARTER.MVS.EXEC
* IPLB13 * SHR KEEP ISPF.SISPEXEC.VB
* VIO NEW DELETE ISPLST1 SYS02190.T085429.RA000.BCARTER.R0100274
* IPLB13 * SHR KEEP * ISPMLIB ISPF.SISPMENU
* SMS278 * SHR KEEP SHARE.ANALYZ21.SIDIMLIB
* SHR89A * SHR KEEP SHARE.ISPMLIB
* SMS25F * SHR KEEP * ISPPLIB SHARE.PROD.ISPPLIB
* SMS891 * SHR KEEP SHARE.ISPPLIB
* SMS25F * SHR KEEP SHARE.ANALYZ21.SIDIPLIB
* IPLB13 * SHR KEEP ISPF.SISPPENU
* IPLB13 * SHR KEEP SDSF.SISFPLIB
* IPLB13 * SHR KEEP SYS1.SBPXPENU
* COD002 * OLD KEEP * ISPPROF BCARTER.ISPPROF
* NEW DELETE SYSIN TERMINAL
* NEW DELETE SYSOUT TERMINAL
* NEW DELETE SYSPRINT TERMINAL

```

The following list describes each column:

1 VOLUME

The volume serial of the DASD volume that contains the data set.

2 CAT

An asterisk in this column indicates that the data set was located by using the system catalog.

3 DISP

The disposition that is assigned to the data set.

4 OPEN

An asterisk in this column indicates that the file is currently open.

5 DDNAME

DD name for the file.

6 DSNAME

Data set name for a DASD data set:

- DUMMY for a DD DUMMY
- SYSOUT(x) for a SYSOUT data set
- TERMINAL for a file allocated to the terminal
- * for a DD * file

You can allocate files to an existing, cataloged data set by using the ALLOCATE command.

You can free an allocated file by using the FREE command.

By default, the DESCRIBE ALLOCATIONS command lists the files allocated by the current user. You can specify other parameters to list other system allocations, such as the data sets currently allocated to LINK list, LPA list, APF list, system catalogs, Parmlib, and Proclib. The *Debug Tool for z/OS Reference and Messages* describes the parameters you must specify to list this information.

Displaying error numbers for messages in the Log window

When an error message shows up in the Log window without a message ID, you can have the message ID show up as in:

EQA1807E The command element d is ambiguous.

Either modify your profile or use the SET MSGID ON command. To modify your profile, use the PANEL PROFILE command and set **Show message ID numbers** to YES by typing over the NO.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Customizing profile settings” on page 197

Finding a renamed source, listing, or separate debug file

If the source, listing, or separate debug file has been renamed since your program was compiled, Debug Tool will not be able to find it, and it will not appear in the Source window when you debug your program.

To point Debug Tool to the renamed file:

- Use the Source Identification panel to direct Debug Tool to the new files:
 1. With the cursor on the command line, press PF4 (LIST).
In the Source Identification panel, you can associate the source, listings, or separate debug files that show in the Source window with their compile units.
 2. Type over the **Listing/Source File** field with the new name.
- Use the SET SOURCE or SET DEFAULT LISTINGS commands to direct Debug Tool to the new files:
 1. With the cursor on the command line, type SET SOURCE ON (*cuname*) *new_file_name*, where *new_file_name* is the renamed source file. Press Enter.
 2. With the cursor on the command line, type SET DEFAULT LISTINGS *new_file_name*, where *new_file_name* is the renamed listing or separate debug file. Press Enter.

To point Debug Tool to several renamed files, you can use the SET DEFAULT LISTINGS command and specify the renamed files, separated by commas and enclosed in parenthesis. For example, to point Debug Tool to the files SVTRSAMP.TS99992.MYPROG, PGRSAMP.LLTEST.PROGA, and RRSAMP.CRTEST.PROGR, enter the following command:

```
SET DEFAULT LISTINGS (SVTRSAMP.TS99992.MYPROG, PGRSAMP.LLTEST.PROGA, RRSAMP.CRTEST.PROGR) ;
```

If you need to do this repeatedly, use one of the following methods:

- Note the SET SOURCE ON commands generated in the Log window. You can save these commands in a file and reissue them with the USE command for future invocations of Debug Tool.
- Use the EQADEBUG DD statement to define the location of the files.
- Code the EQAUEDAT user exit with the location of the files.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Requesting an attention interrupt during interactive sessions

During an interactive Debug Tool session, you can request an attention interrupt, if necessary. For example, you can stop what appears to be an unending loop, stop the display of voluminous output at your terminal, or stop the execution of the STEP command.

An attention interrupt should not be confused with the ATTENTION condition. If you set an AT OCCURRENCE or ON ATTENTION, the commands associated with that breakpoint are not run at an attention interrupt.

Language Environment TRAP and INTERRUPT run-time options should both be set to ON in order for attention interrupts that are recognized by the host operating system to be also recognized by Language Environment. The *test_level* suboption of the TEST run-time option should *not* be set to NONE.

For CICS and full-screen mode through a VTAM terminal only: An attention interrupt key is not supported in CICS or full-screen mode through a VTAM terminal (remote VTAM session).

For MVS only: For C, when using an attention interrupt, use SET INTERCEPT ON FILE stdout to intercept messages to the terminal. This is required because messages do not go to the terminal after an attention interrupt.

For the Dynamic Debug facility only: The Dynamic Debug facility does not support attention interrupts for programs that have been compiled with the TEST(NONE,SYM) compiler option, assembler programs, and disassembly programs.

The correct key might not be marked ATTN on every keyboard. Often the following keys are used:

- Under TSO: PA1 key
- Under IMS: PA1 key

When you request an *attention interrupt*, control is given to Debug Tool:

- At the next hook if Debug Tool has previously gained control or if you specified either TEST(ERROR) or TEST(ALL) or have specifically set breakpoints
- At a `__ctest()` or CEETEST call
- When an HLL condition is raised in the program, such as SIGINT in C

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Starting a debugging session in full-screen mode through a VTAM terminal” on page 103

Related references

z/OS Language Environment Programming Guide

Ending a full-screen debug session

When you have finished debugging your program, you can end your full-screen debug session by using one of the following methods:

Method A

1. Press PF3 (QUIT) or enter QUIT on the command line. If you are debugging a CICS non-Language Environment assembler or OS/VS COBOL program, QUIT end Debug Tool and the task ends with an ABEND 4038.
2. Type Y to confirm your request and press Enter. Your program stops running.

Method B

1. Enter the QQUIT command. You are not prompted to confirm your request to end your debug session. Your program stops running.

Method C

1. Enter the QUIT DEBUG command.
2. Type Y to confirm your request and press Enter. Your program continues to run.

As the program runs, it cannot restart Debug Tool. To restart Debug Tool you must stop running the program and restart your full-screen debug session.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Debug Tool for z/OS Reference and Messages

Chapter 23. Debugging a COBOL program in full-screen mode

The descriptions of basic debugging tasks for COBOL refer to the following COBOL program.

“Example: sample COBOL program for debugging”

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 31, “Debugging COBOL programs,” on page 209

“Halting when certain routines are called in COBOL” on page 140

“Modifying the value of a COBOL variable” on page 141

“Halting on a COBOL line only if a condition is true” on page 142

“Debugging COBOL when only a few parts are compiled with TEST” on page 143

“Capturing COBOL I/O to the system console” on page 143

“Displaying raw storage in COBOL” on page 144

“Getting a COBOL routine traceback” on page 144

“Tracing the run-time path for COBOL code compiled with TEST” on page 144

“Generating a COBOL run-time paragraph trace” on page 145

“Finding unexpected storage overwrite errors in COBOL” on page 146

“Halting before calling an invalid program in COBOL” on page 146

Related references

“Format for a COBOL source listing and debug file” on page 209

Example: sample COBOL program for debugging

The program below is used in various topics to demonstrate debugging tasks.

This program calls two subprograms to calculate a loan payment amount and the future value of a series of cash flows. Several COBOL intrinsic functions are utilized.

Main program COBCALC

```
*****
* COBCALC                                     *
*                                           *
* A simple program that allows financial functions to *
* be performed using intrinsic functions.           *
*                                           *
*****
IDENTIFICATION DIVISION.
PROGRAM-ID. COBCALC.
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
01  PARM-1.
    05  CALL-FEEDBACK      PIC XX.
01  FIELDS.
    05  INPUT-1            PIC X(10).
01  INPUT-BUFFER-FIELDS.
    05  BUFFER-PTR        PIC 9.
    05  BUFFER-DATA.
        10  FILLER        PIC X(10)  VALUE "LOAN".
        10  FILLER        PIC X(10)  VALUE "PVALUE".
```



```

        10 FILLER          PIC X(10)  VALUE "pvalue".
        10 FILLER          PIC X(10)  VALUE "END".
    05  BUFFER-ARRAY      REDEFINES BUFFER-DATA
                           OCCURS 4 TIMES
                           PIC X(10).

PROCEDURE DIVISION.
    DISPLAY "CALC Begins." UPON CONSOLE.
    MOVE 1 TO BUFFER-PTR.
    MOVE SPACES TO INPUT-1.
* Keep processing data until END requested
    PERFORM ACCEPT-INPUT UNTIL INPUT-1 EQUAL TO "END".
* END requested
    DISPLAY "CALC Ends." UPON CONSOLE.
    GOBACK.
* End of program.

*
* Accept input data from buffer
*
ACCEPT-INPUT.
    MOVE BUFFER-ARRAY (BUFFER-PTR) TO INPUT-1.
    ADD 1 BUFFER-PTR GIVING BUFFER-PTR.
* Allow input data to be in UPPER or lower case
    EVALUATE FUNCTION UPPER-CASE(INPUT-1) CALC1 WHEN "END"
        MOVE "END" TO INPUT-1
        WHEN "LOAN"
            PERFORM CALCULATE-LOAN
        WHEN "PVALUE"
            PERFORM CALCULATE-VALUE
        WHEN OTHER
            DISPLAY "Invalid input: " INPUT-1
    END-EVALUATE.

*
* Calculate Loan via CALL to subprogram
*
CALCULATE-LOAN.
    CALL "COBLOAN" USING CALL-FEEDBACK.
    IF CALL-FEEDBACK IS NOT EQUAL "OK" THEN
        DISPLAY "Call to COBLOAN Unsuccessful.".

*
* Calculate Present Value via CALL to subprogram
*
CALCULATE-VALUE.
    CALL "COBVALU" USING CALL-FEEDBACK.
    IF CALL-FEEDBACK IS NOT EQUAL "OK" THEN
        DISPLAY "Call to COBVALU Unsuccessful.".

```

Subroutine COBLOAN

```

*****
* COBLOAN *
* *
* A simple subprogram that calculates payment amount *
* for a loan. *
* *
*****
IDENTIFICATION DIVISION.
PROGRAM-ID. COBLOAN.
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 FIELDS.
    05 INPUT-1          PIC X(26).
    05 PAYMENT          PIC S9(9)V99 USAGE COMP.
    05 PAYMENT-OUT      PIC $$$,$$$,$$9.99 USAGE DISPLAY.
    05 LOAN-AMOUNT      PIC S9(7)V99 USAGE COMP.

```

```

05 LOAN-AMOUNT-IN    PIC X(16).
05 INTEREST-IN       PIC X(5).
05 INTEREST          PIC S9(3)V99 USAGE COMP.
05 NO-OF-PERIODS-IN  PIC X(3).
05 NO-OF-PERIODS     PIC 99 USAGE COMP.
05 OUTPUT-LINE       PIC X(79).
LINKAGE SECTION.
01 PARM-1.
05 CALL-FEEDBACK     PIC XX.
PROCEDURE DIVISION USING PARM-1.
  MOVE "NO" TO CALL-FEEDBACK.
  MOVE "30000 .09 24 " TO INPUT-1.
  UNSTRING INPUT-1 DELIMITED BY ALL " "
    INTO LOAN-AMOUNT-IN INTEREST-IN NO-OF-PERIODS-IN.
* Convert to numeric values
  COMPUTE LOAN-AMOUNT = FUNCTION NUMVAL(LOAN-AMOUNT-IN).
  COMPUTE INTEREST = FUNCTION NUMVAL(INTEREST-IN).
  COMPUTE NO-OF-PERIODS = FUNCTION NUMVAL(NO-OF-PERIODS-IN).
* Calculate annuity amount required
  COMPUTE PAYMENT = LOAN-AMOUNT *
    FUNCTION ANNUITY((INTEREST / 12 ) NO-OF-PERIODS).
* Make it presentable
  MOVE SPACES TO OUTPUT-LINE
  MOVE PAYMENT TO PAYMENT-OUT.
  STRING "COBLOAN: Repayment amount for a " NO-OF-PERIODS-IN
    " month loan of " LOAN-AMOUNT-IN
    " at " INTEREST-IN " interest is: "
    DELIMITED BY SPACES
    INTO OUTPUT-LINE.
  INSPECT OUTPUT-LINE REPLACING ALL "-" BY SPACES.
  DISPLAY OUTPUT-LINE PAYMENT-OUT.
  MOVE "OK" TO CALL-FEEDBACK.
  GOBACK.

```

Subroutine COBVALU

```

*****
* COBVALU                                     *
*                                           *
* A simple subprogram that calculates present value *
* for a series of cash flows.                 *
*                                           *
*****
IDENTIFICATION DIVISION.
PROGRAM-ID. COBVALU.
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 CHAR-DATA.
05 INPUT-1          PIC X(10).
05 PAYMENT-OUT      PIC $$$,$$$,$$9.99 USAGE DISPLAY.
05 INTEREST-IN      PIC X(5).
05 NO-OF-PERIODS-IN PIC X(3).
05 INPUT-BUFFER     PIC X(10) VALUE "5069837544".
05 BUFFER-ARRAY     REDEFINES INPUT-BUFFER
                     OCCURS 5 TIMES
                     PIC XX.
05 OUTPUT-LINE      PIC X(79).
01 NUM-DATA.
05 PAYMENT          PIC S9(9)V99 USAGE COMP.
05 INTEREST          PIC S9(3)V99 USAGE COMP.
05 COUNTER          PIC 99 USAGE COMP.
05 NO-OF-PERIODS     PIC 99 USAGE COMP.
05 VALUE-AMOUNT     OCCURS 99 PIC S9(7)V99 COMP.
LINKAGE SECTION.
01 PARM-1.
05 CALL-FEEDBACK    PIC XX.

```

```

PROCEDURE DIVISION USING PARM-1.
  MOVE "NO" TO CALL-FEEDBACK.
  MOVE ".12 5 " TO INPUT-1.
  UNSTRING INPUT-1 DELIMITED BY "," OR ALL " "
    INTO INTEREST-IN NO-OF-PERIODS-IN.
* Convert to numeric values
  COMPUTE INTEREST = FUNCTION NUMVAL(INTEREST-IN).
  COMPUTE NO-OF-PERIODS = FUNCTION NUMVAL(NO-OF-PERIODS-IN).
* Get cash flows
  PERFORM GET-AMOUNTS VARYING COUNTER FROM 1 BY 1 UNTIL
    COUNTER IS GREATER THAN NO-OF-PERIODS.
* Calculate present value
  COMPUTE PAYMENT =
    FUNCTION PRESENT-VALUE(INTEREST VALUE-AMOUNT(ALL) ).
* Make it presentable
  MOVE PAYMENT TO PAYMENT-OUT.
  STRING "COBVALU: Present_value_for_rate_of_"
    INTEREST-IN " given_amounts_"
    BUFFER-ARRAY (1) " ,_"
    BUFFER-ARRAY (2) " ,_"
    BUFFER-ARRAY (3) " ,_"
    BUFFER-ARRAY (4) " ,_"
    BUFFER-ARRAY (5) " _is:_"
    DELIMITED BY SPACES
    INTO OUTPUT-LINE.
  INSPECT OUTPUT-LINE REPLACING ALL "_" BY SPACES.
  DISPLAY OUTPUT-LINE PAYMENT-OUT.
  MOVE "OK" TO CALL-FEEDBACK.
  GOBACK.
*
* Get cash flows for each period
*
  GET-AMOUNTS.
  MOVE BUFFER-ARRAY (COUNTER) TO INPUT-1.
  COMPUTE VALUE-AMOUNT (COUNTER) = FUNCTION NUMVAL(INPUT-1).

```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 23, “Debugging a COBOL program in full-screen mode,” on page 137

Halting when certain routines are called in COBOL

“Example: sample COBOL program for debugging” on page 137

To halt just before COBLOAN is called, issue the command:

```
AT CALL COBLOAN ;
```

If the CU COBVALU is known to Debug Tool (that is, it has been called previously), to halt just after COBVALU is called, issue the command:

```
AT ENTRY COBVALU ;
```

If the CU COBVALU is not known to Debug Tool (that is, it has not been called previously), to halt just before COBVALU is entered the first time, issue the command:

```
AT APPEARANCE COBVALU ;
```

You can display a list of all compile units that are known to Debug Tool by entering the command:

```
LIST NAMES CUS ;
```

The Debug Tool Log window displays something similar to:

```
LIST NAMES CUS ;  
The following CUs are known in *:  
COBCALC  
COBLOAN  
COBVALU
```

Additionally, you can combine the breakpoints as follows:

```
AT APPEARANCE COBVALU AT ENTRY COBVALU ; GO ;
```

The purpose for the appearance breakpoint is to gain control the **first** time the COBVALU compile unit is run.

To take advantage of either AT ENTRY or AT APPEARANCE, you must compile the routine program (COBVALU in the above example) with the TEST compiler option.

If you have many breakpoints set in your program, you can issue the command:

```
QUERY LOCATION
```

to indicate where in your program execution has been interrupted. The Debug Tool Log window displays something similar to:

```
QUERY LOCATION ;  
You were prompted because STEP ended.  
The program is currently entering block COBVALU.
```

Modifying the value of a COBOL variable

“Example: sample COBOL program for debugging” on page 137

To list the contents of a single variable, move the cursor to an occurrence of the variable name in the Source window and press PF4 (LIST). Remember that Debug Tool starts **after** program initialization but **before** symbolic COBOL variables are initialized, so you cannot view or modify the contents of variables until you have performed a step or run. The value is displayed in the Log window. This is equivalent to entering LIST TITLED *variable* on the command line. Run the COBCALC program to the statement labeled **CALC1**, and enter AT 46 ; GO ; on the Debug Tool command line. Move the cursor over INPUT-1 and press LIST (PF4). The following appears in the Log window:

```
LIST ( INPUT-1 ) ;  
INPUT-1 = 'LOAN'
```

To modify the value of INPUT-1, enter on the command line:

```
MOVE 'pvalue' to INPUT-1 ;
```

You can enter most COBOL expressions on the command line.

Now step into the call to COBVALU by pressing PF2 (STEP) and step until the statement labeled **VALU2** is reached. To view the attributes of the variable INTEREST, issue the Debug Tool command:

```
DESCRIBE ATTRIBUTES INTEREST ;
```

The result in the Log window is:

```
ATTRIBUTES FOR INTEREST  
ITS LENGTH IS 4  
ITS ADDRESS IS 00011DC8  
02 COBVALU:>INTEREST S999V99 COMP
```

You can use this action as a simple browser for group items and data hierarchies. For example, you can list all the values of the elementary items for the CHAR-DATA group with the command:

```
LIST CHAR-DATA ;
```

with results in the Log window appearing something like this:

```
LIST CHAR-DATA ;
02 COBVALU:>INPUT-1 of 01 COBVALU:>CHAR-DATA = '.12 5 '
Invalid data for 02 COBVALU:>PAYMENT-OUT of 01 COBVALU:>CHAR-DATA is found.
02 COBVALU:>INTEREST-IN of 01 COBVALU:>CHAR-DATA = '.12 '
02 COBVALU:>NO-OF-PERIODS-IN of 01 COBVALU:>CHAR-DATA = '5 '
02 COBVALU:>INPUT-BUFFER of 01 COBVALU:>CHAR-DATA = '5069837544'
SUB(1) of 02 COBVALU:>BUFFER-ARRAY of 01 COBVALU:>CHAR-DATA = '50'
SUB(2) of 02 COBVALU:>BUFFER-ARRAY of 01 COBVALU:>CHAR-DATA = '69'
SUB(3) of 02 COBVALU:>BUFFER-ARRAY of 01 COBVALU:>CHAR-DATA = '83'
SUB(4) of 02 COBVALU:>BUFFER-ARRAY of 01 COBVALU:>CHAR-DATA = '75'
SUB(5) of 02 COBVALU:>BUFFER-ARRAY of 01 COBVALU:>CHAR-DATA = '44'
```

Note: If you use the LIST command to list the contents of an uninitialized variable, or a variable that contains invalid data, Debug Tool displays INVALID DATA.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using COBOL variables with Debug Tool” on page 211

Halting on a COBOL line only if a condition is true

Often a particular part of your program works fine for the first few thousand times, but it fails under certain conditions. You don't want to just set a line breakpoint because you will have to keep entering G0.

“Example: sample COBOL program for debugging” on page 137

For example, in COBVALU you want to stop at the calculation of present value only if the discount rate is less than or equal to -1 (before the exception occurs). First run COBCALC, step into COBVALU, and stop at the statement labeled **VALU1**. To accomplish this, issue these Debug Tool commands at the start of COBCALC:

```
AT 67 ; G0 ;
CLEAR AT 67 ; STEP 4 ;
```

Now set the breakpoint like this:

```
AT 44 IF INTEREST > -1 THEN G0 ; END-IF ;
```

Line 44 is the statement labeled **VALU3**. The command causes Debug Tool to stop at line 44. If the value of INTEREST is greater than -1, the program continues. The command causes Debug Tool to remain on line 44 only if the value of INTEREST is less than or equal to -1.

To force the discount rate to be negative, enter the Debug Tool command:

```
MOVE '-2 5' TO INPUT-1 ;
```

Run the program by issuing the G0 command. Debug Tool halts the program at line 44. Display the contents of INTEREST by issuing the LIST INTEREST command. To view the effect of this breakpoint when the discount rate is positive, begin a new debug session and repeat the Debug Tool commands shown in this section.

However, do not issue the MOVE '-2 5' TO INPUT-1 command. The program execution does not stop at line 44 and the program runs to completion.

Debugging COBOL when only a few parts are compiled with TEST

“Example: sample COBOL program for debugging” on page 137

Suppose you want to set a breakpoint at entry to COBVALU. COBVALU has been compiled with TEST but the other programs have not. Debug Tool comes up with an empty Source window. You can use the LIST NAMES CUS command to determine if the COBVALU compile unit is known to Debug Tool and then set the appropriate breakpoint using either the AT APPEARANCE or the AT ENTRY command.

Instead of setting a breakpoint at entry to COBVALU in this example, issue a STEP command when Debug Tool initially displays the empty Source window. Debug Tool runs the program until it reaches the entry for the first routine compiled with TEST, COBVALU in this case.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Halting when certain routines are called in COBOL” on page 140

Capturing COBOL I/O to the system console

To redirect output normally appearing on the system console to your Debug Tool terminal, enter the following command:

```
SET INTERCEPT ON CONSOLE ;
```

“Example: sample COBOL program for debugging” on page 137

For example, if you run COBCALC and issue the Debug Tool SET INTERCEPT ON CONSOLE command, followed by the STEP 3 command, you will see the following output displayed in the Debug Tool Log window:

```
SET INTERCEPT ON CONSOLE ;  
STEP 3 ;  
CONSOLE : CALC Begins.
```

The phrase CALC Begins. is displayed by the statement DISPLAY "CALC Begins." UPON CONSOLE in COBCALC.

The SET INTERCEPT ON CONSOLE command not only captures output to the system console, but also allows you to input data from your Debug Tool terminal instead of the system console by using the Debug Tool INPUT command. For example, if the next COBOL statement executed is ACCEPT INPUT-DATA FROM CONSOLE, the following message appears in the Debug Tool Log window:

```
CONSOLE : IGZ0000I AWAITING REPLY.  
The program is waiting for input from CONSOLE.  
Use the INPUT command to enter 114 characters for the intercepted  
fixed-format file.
```

Continue execution by replying to the input request by entering the following Debug Tool command:

```
INPUT some data ;
```

Note: Whenever Debug Tool intercepts system console I/O, and for the duration of the intercept, the display in the Source window is empty and the Location field in the session panel header at the top of the screen shows *Unknown*.

Displaying raw storage in COBOL

You can display the storage for a variable by using the LIST STORAGE command. For example, to display the storage for the first 12 characters of BUFFER-DATA enter:

```
LIST STORAGE(BUFFER-DATA,12)
```

Getting a COBOL routine traceback

Often when you get close to a programming error, you want to know how you got into that situation, and especially what the traceback of calling routines is. To get this information, issue the command:

```
LIST CALLS ;
```

“Example: sample COBOL program for debugging” on page 137

For example, if you run the COBCALC example with the commands:

```
AT APPEARANCE COBVALU AT ENTRY COBVALU;
GO;
GO;
LIST CALLS;
```

the Log window contains something like:

```
AT APPEARANCE COBVALU
  AT ENTRY COBVALU ;
GO ;
GO ;
LIST CALLS ;
At ENTRY in COBOL program COBVALU.
From LINE 67.1 in COBOL program COBCALC.
```

which shows the traceback of callers.

Tracing the run-time path for COBOL code compiled with TEST

To trace a program showing the entry and exit points without requiring any changes to the program, place the following Debug Tool commands in a file or data set and USE them when Debug Tool initially displays your program. Assuming you have a PDS member, USERID.DT.COMMANDS(COBCALC), that contains the following Debug Tool commands:

```
* Commands in a COBOL USE file must be coded in columns 8-72.
* If necessary, commands can be continued by coding a '-' in
* column 7 of the continuation line.
01 LEVEL PIC 99 USAGE COMP;
MOVE 1 TO LEVEL;
AT ENTRY * PERFORM;
  COMPUTE LEVEL = LEVEL + 1;
  LIST ( "Entry:", LEVEL, %CU);
  GO;
END-PERFORM;
AT EXIT * PERFORM;
  LIST ( "Exit:", LEVEL);
  COMPUTE LEVEL = LEVEL - 1;
  GO;
END-PERFORM;
```

You can use this file as the source of commands to Debug Tool by entering the following command:

```
USE USERID.DT.COMMANDS(COBCALC)
```

If, after executing the USE file, you run COBCALC, the following trace (or similar) is displayed in the Log window:

```
ENTRY:
LEVEL = 00002
%CU = COBCALC
ENTRY:
LEVEL = 00003
%CU = COBLOAN
EXIT:
LEVEL = 00003
ENTRY:
LEVEL = 00003
%CU = COBVALU
EXIT:
LEVEL = 00003
ENTRY:
LEVEL = 00003
%CU = COBVALU
EXIT:
LEVEL = 00003
EXIT:
LEVEL = 00002
```

If you do not want to create the USE file, you can enter the commands through the command line, and the same effect is achieved.

Generating a COBOL run-time paragraph trace

To generate a trace showing the names of paragraphs through which execution has passed, the Debug Tool commands shown in the following example can be used. You can either enter the commands from the Debug Tool command line or place the commands in a file or data set.

“Example: sample COBOL program for debugging” on page 137

Assume you have a PDS member, USERID.DT.COMMANDS(COBCALC2), that contains the following Debug Tool commands.

```
* COMMANDS IN A COBOL USE FILE MUST BE CODED IN COLUMNS 8-72.
* IF NECESSARY, COMMANDS CAN BE CONTINUED BY CODING A '-' IN
* COLUMN 7 OF THE CONTINUATION LINE.
AT GLOBAL LABEL PERFORM;
  LIST LINES %LINE;
  GO;
END-PERFORM;
```

When Debug Tool initially displays your program, enter the following command:

```
USE USERID.DT.COMMANDS(COBCALC2)
```

After executing the USE file, you can run COBCALC and the following trace (or similar) is displayed in the Log window:


```

42      ACCEPT-INPUT.
59      CALCULATE-LOAN.
42      ACCEPT-INPUT.
66      CALCULATE-VALUE.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
42      ACCEPT-INPUT.
66      CALCULATE-VALUE.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
64      GET-AMOUNTS.
42      ACCEPT-INPUT.

```

Finding unexpected storage overwrite errors in COBOL

During program run time, some storage might unexpectedly change its value and you want to find out when and where this happened. Consider this example where the program changes more than the caller expects it to change.

```

05 FIELD-1      OCCURS 2 TIMES
                  PIC X(8).
05 FIELD-2      PIC X(8).
PROCEDURE DIVISION.
*               ( An invalid index value is set )
  MOVE 3 TO PTR.
  MOVE "TOO MUCH" TO FIELD-1( PTR ).

```

Find the address of FIELD-2 with the command:

```
DESCRIBE ATTRIBUTES FIELD-2
```

Suppose the result is X'0000F559'. To set a breakpoint that watches for a change in storage values starting at that address for the next 8 bytes, issue the command:

```
AT CHANGE %STORAGE(H'0000F559',8)
```

When the program runs, Debug Tool halts if the value in this storage changes.

Halting before calling an invalid program in COBOL

Calling an undefined program is a severe error. If you have developed a main program that calls a subprogram that doesn't exist, you can cause Debug Tool to halt just before such a call. For example, if the subprogram NOTYET doesn't exist, you can set the breakpoint:

AT CALL (NOTYET)

When Debug Tool stops at this breakpoint, you can bypass the CALL by entering the GO BYPASS command. This allows you to continue your debug session without raising a condition.

Chapter 24. Debugging an OS/VS COBOL program in full-screen mode

The descriptions of basic debugging tasks for OS/VS COBOL refer to the following program.

“Example: sample OS/VS COBOL program for debugging”

As you read through the information in this document, remember that OS/VS COBOL programs are non-Language Environment programs, even though you might have used Language Environment libraries to link and run your program. Please read the information regarding non-Language Environment programs for instructions on how to start Debug Tool and debug OS/VS COBOL programs, unless OS/VS COBOL-specific information is provided.

Example: sample OS/VS COBOL program for debugging

The program below is used in various topics to demonstrate debugging tasks.

To run this sample program, do the following steps:

1. Prepare the sample program as described in Chapter 6, “Preparing an OS/VS COBOL program,” on page 29.
2. Verify that the debug information for this program is located in the COB03O and COB03AO members of the *yourid*.EQALANGX data set.
3. Start Debug Tool as described in “Programs that start outside of Language Environment” on page 92.
4. To load the debug information for this program, enter the following command:
LDD (COB03O,COB03AO) ;

This program is a small example of an OS/VS COBOL program (COB03O) that calls another OS/VS COBOL program (COB03AO).

Load module: COB03O

COB03O

```
*****
*  PROGRAM NAME: COB03O                               *
*                                                         *
*  COMPILED WITH IBM OS/VS COBOL COMPILER               *
*****

IDENTIFICATION DIVISION.
PROGRAM-ID. COB03O.

*****
*                                                         *
*  LICENSED MATERIALS - PROPERTY OF IBM                  *
*                                                         *
*  5655-M18: Debug Tool for z/OS                         *
*  5655-M19: Debug Tool Utilities and Advanced Functions *
*  (C) Copyright IBM Corp. 2004 All Rights Reserved     *
*                                                         *
*  US GOVERNMENT USERS RESTRICTED RIGHTS - USE, DUPLICATION OR *
*  DISCLOSURE RESTRICTED BY GSA ADP SCHEDULE CONTRACT WITH IBM *
*  CORP.                                                  *
*                                                         *
```

```

*
*
*****
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.

01  LOAN          PIC 999999.
01  INTEREST-RATE PIC 99V99.
01  INTEREST-DUE  PIC 999999.
01  INTEREST-SAVE PIC 999999.
01  INTEREST-AFTER-MULTIPLY PIC 999999.
01  INTEREST-AFTER-DIVIDE PIC 999999.

* DATE THAT WILL RECEIVE INCREMENTED JULIAN-DATE
01  INC-DATE      PIC 9(7).
* LOOP COUNT TO INCREMENT DATE 1000 TIMES *
01  LOOPCOUNT    PIC 9999.

* JULIAN DATE
01  JULIAN-DATE    PIC 9(7).
01  J-DATE REDEFINES JULIAN-DATE.
    05 J-YEAR      PIC 9(4).
    05 J-DAY       PIC 9(3).
* SAVE DATE
01  SAVE-DATE      PIC 9(7).

PROCEDURE DIVISION.

PROG.
    ACCEPT JULIAN-DATE FROM DAY
    DISPLAY 'JULIAN DATE: ' JULIAN-DATE
    MOVE JULIAN-DATE TO SAVE-DATE

    MOVE 10000      TO LOAN

    CALL 'COB03AO' USING LOAN INTEREST-DUE.

    DISPLAY 'LOAN: ' LOAN
    DISPLAY 'INTEREST-DUE: ' INTEREST-DUE

    STOP RUN.

```

COB03AO

```

*****
*  PROGRAM NAME: COB03AO  *
*  *  *  *  *  *  *  *  *
*  COMPILED WITH IBM OS/VS COBOL COMPILER  *
*****

IDENTIFICATION DIVISION.
PROGRAM-ID. COB03AO.

*****
*  *  *  *  *  *  *  *  *
*  LICENSED MATERIALS - PROPERTY OF IBM  *
*  *  *  *  *  *  *  *  *
*  5655-M18: Debug Tool for z/OS  *
*  5655-M19: Debug Tool Utilities and Advanced Functions for z/OS *
*  (C) Copyright IBM Corp. 2004 All Rights Reserved  *
*  *  *  *  *  *  *  *  *
*  US GOVERNMENT USERS RESTRICTED RIGHTS - USE, DUPLICATION OR  *
*  DISCLOSURE RESTRICTED BY GSA ADP SCHEDULE CONTRACT WITH IBM  *
*  CORP.  *
*  *  *  *  *  *  *  *  *
*****

```

```

ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
77 INTEREST-RATE PIC 99V99 VALUE 0.22.
LINKAGE SECTION.
01 USING-LIST.
   02 LOANAMT    PIC 9999999.
   02 INTEREST   PIC 9999999.

PROCEDURE DIVISION USING USING-LIST.

PROG.
  COMPUTE INTEREST = LOANAMT * INTEREST-RATE.
  DISPLAY 'INTEREST-RATE: ' INTEREST-RATE.

GOBACK.

```

Defining a compilation unit as OS/VS COBOL and loading debug information

Before you can debug an OS/VS COBOL program, you must define the compilation unit (CU) as an OS/VS COBOL CU and load the debug data for the CU. This can only be done for a CU that is currently known to Debug Tool as a disassembly CU or for a CU that is not currently known to Debug Tool.

You use the LOADDEBUGDATA command (abbreviated as LDD) to define a disassembly CU as an OS/VS COBOL CU and to cause the debug data for this CU to be loaded. When you invoke the LDD command, you can specify either a single CU name or a list of CU names enclosed in parenthesis. Each of the names specified must be either:

- the name of a disassembly CU that is currently known to Debug Tool
- a name that does not match the name of a CU currently known to Debug Tool

When the CU name is currently known to Debug Tool, the CU is immediately marked as an OS/VS COBOL CU and an attempt is made to load the debug as follows:

- If your debug data is in a partitioned data set where the high-level qualifier is the current user ID, the low-level qualifier is EQALANGX, and the member name is the same as the name of the CU that you want to debug no other action is necessary
- If your debug data is in a different partitioned data set than userid.EQALANGX but the member name is the same as the name of the CU that you want to debug, enter the following command before or after you enter the LDD command: SET DEFAULT LISTINGS
- If your debug data is in a sequential data set or is a member of a partitioned data set but the member name is different from the CU name, enter the following command before or after the LDD: SET SOURCE

When the CU name specified on the LDD command is not currently known to Debug Tool, a message is issued and the LDD command is deferred until a CU by that name becomes known (appears). At that time, the CU is automatically created as an OS/VS COBOL CU and an attempt is made to load the debug data using the default data set name or the current SET DEFAULT LISTINGS specification.

After you have entered an LDD command for a CU, you cannot view the CU as a disassembly CU.

If Debug Tool cannot find the associated debug data after you have entered an LDD command, the CU is an OS/VS COBOL CU rather than a disassembly CU. You cannot enter another LDD command for this CU. However, you can enter a SET DEFAULT LISTING command or a SET SOURCE command to cause the associated debug data to be loaded from a different data set.

Defining a compilation unit in a different load module as OS/VS COBOL

You must use the LDD command to identify a CU as an OS/VS COBOL CU. If the CU is part of a load module that has not yet been loaded when you enter the LDD command, Debug Tool displays a message indicating that the CU was not found and that the running of the LDD command has been deferred. If the CU later appears as a disassembly CU, the LDD command is run at that time.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Defining a compilation unit as OS/VS COBOL and loading debug information” on page 151

Halting when certain OS/VS COBOL programs are called

“Example: sample OS/VS COBOL program for debugging” on page 149

To halt after the COB03AO routine is called, enter the following command:

```
AT ENTRY COB03AO ;
```

The AT CALL command is not supported for OS/VS COBOL routines. Do not use the AT CALL command to halt Debug Tool when an OS/VS COBOL routine is called.

If you have many breakpoints set in your program and you want to know where your program was halted, you can enter the following command:

```
QUERY LOCATION
```

The Debug Tool Log window displays a message similar to the following message:

```
QUERY LOCATION
```

```
You are executing commands in the ENTRY COB030 ::> COB03AO breakpoint.  
The program is currently entering block COB030 ::> COB03AO.
```

Displaying and modifying the value of OS/VS COBOL variables or storage

To display the contents of a single variable, move the cursor to an occurrence of the variable name in the Source window and press PF4 (LIST). The value is displayed in the Log window. This is equivalent to entering the LIST *variable* command on the command line.

For example, run the COB03O program to the CALL statement by entering AT 56 ; GO ; on the Debug Tool command line. Move the cursor over LOAN and press PF4 (LIST). Debug Tool displays the following message in the Log window:

```
LIST ( 'LOAN ' )  
LOAN = 10000
```

To change the value of LOAN to 100, type 'LOAN' = '100' in the command line and press Enter.

To view the attributes of variable LOAN, enter the following command:

```
DESCRIBE ATTRIBUTES LOAN
```

Debug Tool displays the following messages in the Log window:

```
ATTRIBUTES for LOAN
  Its address is 0002E500 and its length is 6
  LOAN PIC 999999
```

To step into the call to COB03AO, press PF2 (STEP).

Halting on a line in OS/VS COBOL only if a condition is true

Often a particular part of your program works fine for the first few thousand times, but it fails under certain conditions. Setting a line breakpoint is inefficient because you will have to repeatedly enter the GO command.

“Example: sample OS/VS COBOL program for debugging” on page 149

In the COB03AO program, to halt Debug Tool when the LOANAMT variable is set to 100, enter the following command:

```
AT 36 DO; IF 'LOANAMT ^= 100' THEN GO; END;
```

Line 36 is the line COMPUTE INTEREST = LOANAMT * INTEREST-RATE. The command causes Debug Tool to stop at line 36. If the value of LOANAMT is not 100, the program continues. The command causes Debug Tool to stop on line 36 only if the value of LOANAMT is 100.

Debugging OS/VS COBOL when debug information is only available for a few parts

“Example: sample OS/VS COBOL program for debugging” on page 149

Suppose you want to set a breakpoint at the entry point to COB03AO program and that debug information is available for COB03AO but not for COB03O. In this circumstance, Debug Tool would display an empty Source window. To display a list of compile units known to Debug Tool, enter the following commands:

```
SET ASSEMBLER ON
LIST NAMES CUS
```

The LIST NAMES CUS command displays a list of all the compile units that are known to Debug Tool. If COB03AO is fetched later on by the application, it might not be known to Debug Tool. Enter the following commands:

```
LDD COB03AO
AT ENTRY COB03AO
GO
```

Getting an OS/VS COBOL program traceback

Often when you get close to a programming error, you want to know what sequence of calls lead you to the programming error. This sequence is called a traceback or a traceback of callers. To get the traceback information, enter the following command:

LIST CALLS

“Example: sample OS/VS COBOL program for debugging” on page 149

For example, if you run the example with the following commands, the Log window displays the traceback of callers:

```
LDD (COB030,COB03A0) ;  
AT ENTRY COB03A0 ;  
GO ;  
LIST CALLS ;
```

The Log window displays information similar to the following:

```
At ENTRY in OS/VS COBOL program COB030 ::> COB03A0.  
From LINE 74 in OS/VS COBOL program COB030 ::> COB030.
```

Finding unexpected storage overwrite errors in OS/VS COBOL

While your program is running, some storage might unexpectedly change its value and you want to find out when and where this happened. Suppose in the example described in “Getting an OS/VS COBOL program traceback” on page 153, the program finds the value of LOAN unexpectedly modified. To set a breakpoint that watches for a change in the value of LOAN, enter the following command:

```
AT CHANGE 'LOAN';
```

When the program runs, Debug Tool stops if the value of LOAN changes.

Chapter 25. Debugging a PL/I program in full-screen mode

The descriptions of basic debugging tasks for PL/I refer to the following PL/I program.

“Example: sample PL/I program for debugging”

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 33, “Debugging PL/I programs,” on page 227

“Halting when certain PL/I functions are called” on page 158

“Modifying the value of a PL/I variable” on page 158

“Halting on a PL/I line only if a condition is true” on page 159

“Debugging PL/I when only a few parts are compiled with TEST” on page 159

“Displaying raw storage in PL/I” on page 160

“Getting a PL/I function traceback” on page 160

“Tracing the run-time path for PL/I code compiled with TEST” on page 161

“Finding unexpected storage overwrite errors in PL/I” on page 162

“Halting before calling an undefined program in PL/I” on page 162

Example: sample PL/I program for debugging

The program below is used in various topics to demonstrate debugging tasks.

This program is a simple calculator that reads its input from a character buffer. If integers are read, they are pushed on a stack. If one of the operators (+ - * /) is read, the top two elements are popped off the stack, the operation is performed on them and the result is pushed on the stack. The = operator writes out the value of the top element of the stack to a buffer.

Before running PLICALC, you need to allocate SYSPRINT to the terminal by entering the following command:

```
ALLOC FI(SYSPRINT) DA(*) REUSE
```

Main program PLICALC

```
plicalc: proc options(main);
/*-----*/
/*
/* A simple calculator that does operations on integers that
/* are pushed and popped on a stack
/*
/*-----*/
dcl index builtin;
dcl length builtin;
dcl substr builtin;
/*
dcl 1 stack,
    2 stkptr fixed bin(15,0) init(0),
    2 stknum(50) fixed bin(31,0);
dcl 1 bufin,
    2 bufptr fixed bin(15,0) init(0),
    2 bufchr char (100) varying;
dcl 1 tok char (100) varying;
dcl 1 tstop char(1) init ('s');
dcl 1 ndx fixed bin(15,0);
```

```

dcl num      fixed bin(31,0);
dcl i        fixed bin(31,0);
dcl push entry external;
dcl pop  entry returns (fixed bin(31,0)) external;
dcl readtok entry returns (char (100) varying) external;
/*-----*/
/* input  action:                                     */
/*  2      push 2 on stack                             */
/*  18     push 18                                     */
/*  +      pop 2, pop 18, add, push result (20)         */
/*  =      output value on the top of the stack (20)   */
/*  5      push 5                                     */
/*  /      pop 5, pop 20, divide, push result (4)      */
/*  =      output value on the top of the stack (4)    */
/*-----*/
bufchr = '2 18 + = 5 / =';
do while (tok ^= tstop);
  tok = readtok(bufin);          /* get next 'token' */
  select (tok);
    when (tstop)
      leave;
    when ('+') do;
      num = pop(stack);
      call push(stack,num);      /* CALC1  statement */
    end;
    when ('-') do;
      num = pop(stack);
      call push(stack,pop(stack)-num);
    end;
    when ('*')
      call push(stack,pop(stack)*pop(stack));
    when ('/') do;
      num = pop(stack);
      call push(stack,pop(stack)/num); /* CALC2  statement */
    end;
    when ('=') do;
      num = pop(stack);
      put list ('PLICALC: ', num) skip;
      call push(stack,num);
    end;
    otherwise do; /* must be an integer */
      num = atoi(tok);
      call push(stack,num);
    end;
  end;
end;
return;

```

TOK function

```

atoi: procedure(tok) returns (fixed bin(31,0));
/*-----*/
/*
/* convert character string to number
/* (note: string validated by readtok)
/*
/*-----*/
dcl 1 tok char (100) varying;
dcl 1 num fixed bin (31,0);
dcl 1 j fixed bin(15,0);
num = 0;
do j = 1 to length(tok);
  num = (10 * num) + (index('0123456789',substr(tok,j,1))-1);
end;
return (num);
end atoi;
end plicalc;

```

PUSH function

```
push: procedure(stack,num);
/*-----*/
/*
/* a simple push function for a stack of integers
/*
/*
/*-----*/
dcl 1 stack connected,
      2 stkptr fixed bin(15,0),
      2 stknum(50) fixed bin(31,0);
dcl num      fixed bin(31,0);
stkptr = stkptr + 1;
stknum(stkptr) = num; /* PUSH1 statement */
return;
end push;
```

POP function

```
pop: procedure(stack) returns (fixed bin(31,0));
/*-----*/
/*
/* a simple pop function for a stack of integers
/*
/*
/*-----*/
dcl 1 stack connected,
      2 stkptr fixed bin(15,0),
      2 stknum(50) fixed bin(31,0);
stkptr = stkptr - 1;
return (stknum(stkptr+1));
end pop;
```

READTOK function

```
readtok: procedure(bufin) returns (char (100) varying);
/*-----*/
/*
/* a function to read input and tokenize it for a simple calculator
/*
/*
/* action: get next input char, update index for next call
/* return: next input char(s)
/*
/*-----*/
dcl length builtin;
dcl substr builtin;
dcl verify builtin;
dcl 1 bufin connected,
      2 bufptr fixed bin(15,0),
      2 bufchr char (100) varying;
dcl 1 tok char (100) varying;
dcl 1 tstop char(1) init ('s');
dcl 1 j fixed bin(15,0);

/* start of processing */
if bufptr > length(bufchr) then do;
  tok = tstop;
  return ( tok );
end;
bufptr = bufptr + 1;
do while (substr(bufchr,bufptr,1) = ' ');
  bufptr = bufptr + 1;
  if bufptr > length(bufchr) then do;
    tok = tstop;
    return ( tok );
  end;
end;
tok = substr(bufchr,bufptr,1); /* get ready to return single char */
select (tok);
  when ('+', '-', '/', '*', '=')
    bufptr = bufptr;
```

```

otherwise do;                                /* possibly an integer */
  tok = '';
  do j = bufptr to length(bufchr);
    if verify(substr(bufchr,j,1),'0123456789') ^= 0 then
      leave;
  end;
  if j > bufptr then do;
    j = j - 1;
    tok = substr(bufchr,bufptr,(j-bufptr+1));
    bufptr = j;
  end;
  else
    tok = tstop;
  end;
end;
return (tok);
end readtok;

```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 25, “Debugging a PL/I program in full-screen mode,” on page 155

Halting when certain PL/I functions are called

“Example: sample PL/I program for debugging” on page 155

To halt just before READTOK is called, issue the command:

```
AT CALL READTOK ;
```

To halt just after READTOK is called, issue the command:

```
AT ENTRY READTOK ;
```

To take advantage of the AT ENTRY command, you must compile your program with the TEST option.

If you have many breakpoints set in your program, you can issue the command:

```
QUERY LOCATION
```

to indicate where in your program execution has been interrupted. The Debug Tool Log window displays something similar to:

```

QUERY LOCATION ;
You are executing commands in the ENTRY READTOK breakpoint.
The program is currently entering block READTOK.

```

Modifying the value of a PL/I variable

To list the contents of a single variable, move the cursor to an occurrence of the variable name in the Source window and press PF4 (LIST). The value is displayed in the Log window. This is equivalent to entering LIST TITLED variable on the command line. For example, run the PLICALC program to the statement labeled **CALC1** by entering AT 22 ; G0 ; on the Debug Tool command line. Move the cursor over NUM and press PF4 (LIST). The following appears in the Log window:

```

LIST NUM ;
NUM =                18

```

To modify the value of NUM to 22, type over the NUM = 18 line with NUM = 22, press Enter to put it on the command line, and press Enter again to issue the command.

You can enter most PL/I expressions on the command line.

Now step into the call to PUSH by pressing PF2 (STEP) and step until the statement labeled **PUSH1** is reached. To view the attributes of variable STKNUM, enter the Debug Tool command:

```
DESCRIBE ATTRIBUTES STKNUM;
```

Note: If you are debugging an Enterprise PL/I program, you cannot use the DESCRIBE ATTRIBUTES command.

The result in the Log window is:

```
ATTRIBUTES FOR STKNUM
ITS ADDRESS IS 0003944C AND ITS LENGTH IS 200
PUSH : STACK.STKNUM(50) FIXED BINARY(31,0) REAL PARAMETER
ITS ADDRESS IS 0003944C AND ITS LENGTH IS 4
```

You can list all the values of the members of the structure pointed to by STACK with the command:

```
LIST STACK;
```

with results in the Log window appearing something like this:

```
LIST STACK ;
STACK.STKPTR =                2
STACK.STKNUM(1) =              2
STACK.STKNUM(2) =              18
STACK.STKNUM(3) =             233864
      ⋮
STACK.STKNUM(50) =             121604
```

You can change the value of a structure member by issuing the assignment as a command as in the following example:

```
STKNUM(STKPTR) = 33;
```

Halting on a PL/I line only if a condition is true

Often a particular part of your program works fine for the first few thousand times, but it fails under certain conditions. You don't want to just set a line breakpoint because you will have to keep entering G0.

"Example: sample PL/I program for debugging" on page 155

For example, in PLICALC you want to stop at the division selection only if the divisor is 0 (before the exception occurs). Set the breakpoint like this:

```
AT 31 DO; IF NUM ^= 0 THEN G0; END;
```

Line 31 is the statement labeled **CALC2**. The command causes Debug Tool to stop at line 31. If the value of NUM is not 0, the program continues. The command causes Debug Tool to stop on line 31 only if the value of NUM is 0.

Debugging PL/I when only a few parts are compiled with TEST

"Example: sample PL/I program for debugging" on page 155

Suppose you want to set a breakpoint at entry to subroutine PUSH. PUSH has been compiled with TEST, but the other files have not. Debug Tool comes up with an empty Source window. To display the compile units, enter the command:

```
LIST NAMES CUS
```

The LIST NAMES CUS command displays a list of all the compile units that are known to Debug Tool. If PUSH is fetched later on by the application, this compile unit might not be known to Debug Tool. If it is displayed, enter:

```
SET QUALIFY CU PUSH  
AT ENTRY PUSH;  
GO ;
```

If it is not displayed, set an appearance breakpoint as follows:

```
AT APPEARANCE PUSH ;  
GO ;
```

You can also combine the breakpoints as follows:

```
AT APPEARANCE PUSH AT ENTRY PUSH; GO;
```

The only purpose for this appearance breakpoint is to gain control the **first** time a function in the PUSH compile unit is run. When that happens, you can set a breakpoint at entry to PUSH like this:

```
AT ENTRY PUSH;
```

Displaying raw storage in PL/I

You can display the storage for a variable by using the LIST STORAGE command. For example, to display the storage for the first 30 characters of STACK enter:

```
LIST STORAGE(STACK,30)
```

Getting a PL/I function traceback

Often when you get close to a programming error, you want to know how you got into that situation, and especially what the traceback of calling functions is. To get this information, issue the command:

```
LIST CALLS ;
```

“Example: sample PL/I program for debugging” on page 155

For example, if you run the PLICALC example with the commands:

```
AT ENTRY READTOK ;  
GO ;  
LIST CALLS ;
```

the Log window will contain something like:

```
At ENTRY IN PL/I subroutine READTOK.  
From LINE 17.1 IN PL/I subroutine PLICALC.
```

which shows the traceback of callers.

Tracing the run-time path for PL/I code compiled with TEST

To trace a program showing the entry and exit points without changing the program, you can enter the commands described in step 2 by using a commands file or by entering the commands individually. To use a commands file, do the following steps:

1. Create a PDS member with a name similar to the following name:
userid.DT.COMMANDS(PLICALL)
2. Edit the file or data set and add the following Debug Tool commands:

```
SET PROGRAMMING LANGUAGE PLI ;
DCL LVLSTR CHARACTER (50);
DCL LVL FIXED BINARY (15);
LVL = 0;
AT ENTRY *
DO;
LVLSTR = ' ' ;
LVL = LVL + 1 ;
LVLSTR = 'ENTERING >' || %BLOCK;
LIST UNTITLED ( LVLSTR ) ;
GO ;
END;
AT EXIT *
DO;
LVLSTR = 'EXITING < ' || %BLOCK;
LIST UNTITLED ( LVLSTR ) ;
LVL = LVL - 1 ;
GO ;
END;
```
3. Start Debug Tool.
4. Enter the following command:
USE DT.COMMANDS(PLICALL)
5. Run your program sequence. Debug Tool displays the trace in the Log window.

For example, after you enter the USE command, you run the following program sequence:

```
*PROCESS MACRO,OPT(TIME);
*PROCESS S STMT TEST(ALL);

PLICALL: PROC OPTIONS (MAIN);

DCL PLIXOPT CHAR(60) VAR STATIC EXTERNAL

INIT('STACK(20K,20K),TEST');

CALL PLISUB;

PUT SKIP LIST('DONE WITH PLICALL');

PLISUB: PROC;

DCL PLISUB1 ENTRY ;

CALL PLISUB1;

PUT SKIP LIST('DONE WITH PLISUB ');

END PLISUB;

PLISUB1: PROC;

DCL PLISUB2 ENTRY ;
```



```

CALL PLISUB2;

PUT SKIP LIST('DONE WITH PLISUB1');

END PLISUB1;

PLISUB2: PROC;

PUT SKIP LIST('DONE WITH PLISUB2');
END PLISUB2;
END PLICALL;

```

In the Log window, Debug Tool displays a trace similar to the following trace:

'ENTERING >PLICALL	
'ENTERING >PLISUB	
'ENTERING >PLISUB1	
'ENTERING >PLISUB2	
'EXITING < PLISUB2	
'EXITING < PLISUB1	
'EXITING < PLISUB	
'EXITING < PLICALL	

Finding unexpected storage overwrite errors in PL/I

During program run time, some storage might unexpectedly change its value and you want to find out when and where this happened. Consider the following example where the program changes more than the caller expects it to change.

```

2 FIELD1(2) CHAR(8);
2 FIELD2 CHAR(8);
  CTR = 3;          /* an invalid index value is set */
  FIELD1(CTR) = 'TOO MUCH';

```

Find the address of FIELD2 with the command:

```
DESCRIBE ATTRIBUTES FIELD2
```

Suppose the result is X'00521D42'. To set a breakpoint that watches for a change in storage values starting at that address for the next 8 bytes, issue the command:

```
AT CHANGE %STORAGE('00521D42'px,8)
```

When the program is run, Debug Tool halts if the value in this storage changes.

Halting before calling an undefined program in PL/I

Calling an undefined program or function is a severe error. To halt just before such a call is run, set this breakpoint:

```
AT CALL 0
```

When Debug Tool stops at this breakpoint, you can bypass the CALL by entering the GO BYPASS command. This allows you to continue your debug session without raising a condition.

Chapter 26. Debugging a C program in full-screen mode

The descriptions of basic debugging tasks for C refer to the following C program.

“Example: sample C program for debugging”

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 34, “Debugging C and C++ programs,” on page 237

“Halting when certain functions are called in C” on page 166

“Modifying the value of a C variable” on page 166

“Halting on a line in C only if a condition is true” on page 167

“Debugging C when only a few parts are compiled with TEST” on page 168

“Capturing C output to stdout” on page 168

“Calling a C function from Debug Tool” on page 168

“Displaying raw storage in C” on page 169

“Debugging a C DLL” on page 169

“Getting a function traceback in C” on page 169

“Tracing the run-time path for C code compiled with TEST” on page 170

“Finding unexpected storage overwrite errors in C” on page 170

“Finding uninitialized storage errors in C” on page 171

“Halting before calling a NULL C function” on page 172

Example: sample C program for debugging

The program below is used in various topics to demonstrate debugging tasks.

This program is a simple calculator that reads its input from a character buffer. If integers are read, they are pushed on a stack. If one of the operators (+ - * /) is read, the top two elements are popped off the stack, the operation is performed on them, and the result is pushed on the stack. The = operator writes out the value of the top element of the stack to a buffer.

CALC.H

```
/*----- FILE CALC.H -----*/
/*
/* Header file for CALC.C PUSHPOP.C READTKN.C
/* a simple calculator
/*-----*/
typedef enum toks {
    T_INTEGER,
    T_PLUS,
    T_TIMES,
    T_MINUS,
    T_DIVIDE,
    T_EQUALS,
    T_STOP
} Token;
Token read_token(char buf[]);
typedef struct int_link {
    struct int_link * next;
    int i;
} IntLink;
typedef struct int_stack {
```

```

    IntLink * top;
} IntStack;
extern void push(IntStack *, int);
extern int pop(IntStack *);

```

CALC.C

```

/*----- FILE CALC.C -----*/
/*
/* A simple calculator that does operations on integers that
/* are pushed and popped on a stack
/*-----*/
#include <stdio.h>
#include <stdlib.h>
#include "calc.h"
IntStack stack = { 0 };
main()
{
    Token tok;
    char word[100];
    char buf_out[100];
    int num, num2;
    for(;;)
    {
        tok=read_token(word);
        switch(tok)
        {
            case T_STOP:
                break;
            case T_INTEGER:
                num = atoi(word);
                push(&stack,num);    /* CALC1 statement */
                break;
            case T_PLUS:
                push(&stack, pop(&stack)+pop(&stack) );
                break;
            case T_MINUS:
                num = pop(&stack);
                push(&stack, num-pop(&stack));
                break;
            case T_TIMES:
                push(&stack, pop(&stack)*pop(&stack));
                break;
            case T_DIVIDE:
                num2 = pop(&stack);
                num = pop(&stack);
                push(&stack, num/num2);    /* CALC2 statement */
                break;
            case T_EQUALS:
                num = pop(&stack);
                sprintf(buf_out,"= %d ",num);
                push(&stack,num);
                break;
        }
        if (tok==T_STOP)
            break;
    }
    return 0;
}

```

PUSHPOP.C

```

/*----- FILE PUSHPOP.C -----*/
/*
/* A push and pop function for a stack of integers
/*-----*/
#include <stdlib.h>
#include "calc.h"

```

```

/*-----*/
/* input:  stk - stack of integers */
/*        num - value to push on the stack */
/* action: get a link to hold the pushed value, push link on stack */
/*-----*/
extern void push(IntStack * stk, int num)
{
    IntLink * ptr;
    ptr      = (IntLink *) malloc( sizeof(IntLink)); /* PUSHPOP1 */
    ptr->i    = num;                               /* PUSHPOP2 statement */
    ptr->next = stk->top;
    stk->top  = ptr;
}
/*-----*/
/* return: int value popped from stack */
/* action: pops top element from stack and gets return value from it */
/*-----*/
extern int pop(IntStack * stk)
{
    IntLink * ptr;
    int num;
    ptr      = stk->top;
    num      = ptr->i;
    stk->top  = ptr->next;
    free(ptr);
    return num;
}

```

READTKN.C

```

/*----- FILE READTKN.C -----*/
/*
/* A function to read input and tokenize it for a simple calculator */
/*-----*/
#include <ctype.h>
#include <stdio.h>
#include "calc.h"
/*-----*/
/* action: get next input char, update index for next call */
/* return: next input char */
/*-----*/
static char nextchar(void)
{
    /*-----*/
    /* input  action: */
    /* 2      push 2 on stack */
    /* 18     push 18 */
    /* +      pop 2, pop 18, add, push result (20) */
    /* =      output value on the top of the stack (20) */
    /* 5      push 5 */
    /* /      pop 5, pop 20, divide, push result (4) */
    /* =      output value on the top of the stack (4) */
    /*-----*/
    char * buf_in = "2 18 + = 5 / = ";
    static int index; /* starts at 0 */
    char ret;
    ret = buf_in[index];
    ++index;
    return ret;
}
/*-----*/
/* output: buf - null terminated token */
/* return: token type */
/* action: reads chars through nextchar() and tokenizes them */
/*-----*/
Token read_token(char buf[])

```

```

{
    int i;
    char c;
    /* skip leading white space */
    for( c=nextchar();
        isspace(c);
        c=nextchar())
        ;
    buf[0] = c; /* get ready to return single char e.g. "+" */
    buf[1] = 0;
    switch(c)
    {
        case '+' : return T_PLUS;
        case '-' : return T_MINUS;
        case '*' : return T_TIMES;
        case '/' : return T_DIVIDE;
        case '=' : return T_EQUALS;
        default:
            i = 0;
            while (isdigit(c)) {
                buf[i++] = c;
                c = nextchar();
            }
            buf[i] = 0;
            if (i==0)
                return T_STOP;
            else
                return T_INTEGER;
    }
}

```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 26, “Debugging a C program in full-screen mode,” on page 163

Halting when certain functions are called in C

“Example: sample C program for debugging” on page 163

To halt just before `read_token` is called, issue the command:

```
AT CALL read_token ;
```

To halt just after `read_token` is called, issue the command:

```
AT ENTRY read_token ;
```

To take advantage of either of the above actions, you must compile your program with the `TEST` compiler option.

Modifying the value of a C variable

To `LIST` the contents of a single variable, move the cursor to the variable name and press `PF4` (`LIST`). The value is displayed in the Log window. This is equivalent to entering `LIST TITLED variable` on the command line.

“Example: sample C program for debugging” on page 163

Run the `CALC` program above to the statement labeled **CALC1**, move the cursor over `num` and press `PF4` (`LIST`). The following appears in the Log window:

```
LIST ( num ) ;  
num = 2
```

To modify the value of *num* to 22, type over the *num* = 2 line with *num* = 22, press Enter to put it on the command line, and press Enter again to issue the command.

You can enter most C expressions on the command line.

Now step into the call to *push()* by pressing PF2 (STEP) and step until the statement labeled PUSHPOP2 is reached. To view the attributes of variable *ptr*, issue the Debug Tool command:

```
DESCRIBE ATTRIBUTES *ptr;
```

The result in the Log window is similar to the following:

```
ATTRIBUTES for * ptr  
Its address is 0BB6E010 and its length is 8  
  struct int_link  
    struct int_link *next;  
    int i;
```

You can use this action to browse structures and unions.

You can list all the values of the members of the structure pointed to by *ptr* with the command:

```
LIST *ptr ;
```

with results in the Log window appearing similar to the following:

```
LIST * ptr ;  
(* ptr).next = 0x00000000  
(* ptr).i = 0
```

You can change the value of a structure member by issuing the assignment as a command as in the following example:

```
(* ptr).i = 33 ;
```

Halting on a line in C only if a condition is true

Often a particular part of your program works fine for the first few thousand times, but fails afterwards because a specific condition is present. Setting a simple line breakpoint is an inefficient way to debug the program because you need to execute the G0 command a thousand times to reach the specific condition. You can instruct Debug Tool to continue executing a program until a specific condition is present.

“Example: sample C program for debugging” on page 163

For example, in the *main* procedure of the program above, you want to stop at T_DIVIDE only if the divisor is 0 (before the exception occurs). Set the breakpoint like this:

```
AT 40 { if(num2 != 0) G0; }
```

Line 40 is the statement labeled **CALC2**. The command causes Debug Tool to stop at line 40. If the value of *num2* is not 0, the program continues. You can enter Debug Tool commands to change the value of *num2* to a nonzero value.

Debugging C when only a few parts are compiled with TEST

“Example: sample C program for debugging” on page 163

Suppose you want to set a breakpoint at entry to the function `push()` in the file `PUSHPOP.C`. `PUSHPOP.C` has been compiled with `TEST` but the other files have not. Debug Tool comes up with an empty Source window. To display the compile units, enter the command:

```
LIST NAMES CUS
```

The `LIST NAMES CUS` command displays a list of all the compile units that are known to Debug Tool. Depending on the compiler you are using, or if `"USERID.MFISTART.C(PUSHPOP)"` is fetched later on by the application, this compile unit might not be known to Debug Tool. If it is displayed, enter:

```
SET QUALIFY CU "USERID.MFISTART.C(PUSHPOP)"
AT ENTRY push;
GO ;
```

or

```
AT ENTRY "USERID.MFISTART.C(PUSHPOP)":>push
GO;
```

If it is not displayed, set an appearance breakpoint as follows:

```
AT APPEARANCE "USERID.MFISTART.C(PUSHPOP)" ;
GO ;
```

The only purpose for this appearance breakpoint is to gain control the first time a function in the `PUSHPOP` compile unit is run. When that happens, you can set breakpoints at entry to `push()`:

```
AT ENTRY push;
```

You can also combine the breakpoints as follows:

```
AT APPEARANCE "USERID.MFISTART.C(PUSHPOP)" AT ENTRY push; GO;
```

Capturing C output to stdout

To redirect stdout to the Log window, issue the following command:

```
SET INTERCEPT ON FILE stdout ;
```

With this `SET` command, you will capture not only stdout from your program, but also from interactive function calls. For example, you can interactively call `printf` on the command line to display a null-terminated string by entering:

```
printf(sptr);
```

You might find this easier than using `LIST STORAGE`.

Calling a C function from Debug Tool

You can start a library function (such as `strlen`) or one of the program functions interactively by calling it on the command line.

“Example: sample C program for debugging” on page 163

Below, we call `push()` interactively to push one more value on the stack just before a value is popped off.

```
AT CALL pop ;
GO ;
push(77);
GO ;
```

The calculator produces different results than before because of the additional value pushed on the stack.

Displaying raw storage in C

A `char *` variable *ptr* can point to a piece of storage containing printable characters. To display the first 20 characters enter:

```
LIST STORAGE(*ptr,20)
```

If the string is null terminated, you can also use an interactive function call on the command line, as in:

```
puts(ptr) ;
```

Debugging a C DLL

“Example: sample C program for debugging” on page 163

Build PUSHPOP.C as a DLL, exporting `push()` and `pop()`. Build CALC.C and READTOKN.C as the program that imports `push()` and `pop()` from the DLL named PUSHPOP. When the application CALC starts the DLL, PUSHPOP will not be known to Debug Tool. Use the AT APPEARANCE breakpoint to gain control in the DLL the first time code in that compile unit appears, as shown in the following example:

```
AT APPEARANCE "USERID.MFISTART.C(PUSHPOP)" ;
GO ;
```

The only purpose of this appearance breakpoint is to gain control the first time a function in the PUSHPOP compile unit is run. When this happens, you can set breakpoints in PUSHPOP.

Getting a function traceback in C

Often when you get close to a programming error, you want to know how you got into that situation, and especially what the traceback of calling functions is. To get this information, issue the command:

```
LIST CALLS ;
```

“Example: sample C program for debugging” on page 163

For example, if you run the CALC example with the commands:

```
AT ENTRY read_token ;
GO ;
LIST CALLS ;
```

the Log window will contain something like:

```
At ENTRY in C function CALC ::> "USERID.MFISTART.C(READTOKN)" :> read_token.
From LINE 18 in C function CALC ::> "USERID.MFISTART.C(CALC)" :> main :> %BLOCK2.
```

which shows the traceback of callers.

Tracing the run-time path for C code compiled with TEST

To trace a program showing the entry and exit points without requiring any changes to the program, place the following Debug Tool commands in a file and USE them when Debug Tool initially displays your program. Assuming you have a data set `USERID.DTUSE(TRACE)` that contains the following Debug Tool commands:

```
int indent;
indent = 0;
SET INTERCEPT ON FILE stdout;
AT ENTRY * { \
    ++indent; \
    if (indent < 0) indent = 0; \
    printf("%*.s>%s\n", indent, " ", %block); \
    GO; \
}
AT EXIT * {\
    if (indent < 0) indent = 0; \
    printf("%*.s<%s\n", indent, " ", %block); \
    --indent; \
    GO; \
}
```

You can use this file as the source of commands to Debug Tool by entering the following command:

```
USE USERID.DTUSE(TRACE)
```

The trace of running the program listed below after executing the USE file will be displayed in the Log window.

```
int foo(int i, int j) {
    return i+j;
}
int main(void) {
    return foo(1,2);
}
```

The following trace in the Log window is displayed after running the sample program, with the USE file as a source of input for Debug Tool commands:

```
>main
>foo
<foo
<main
```

If you do not want to create the USE file, you can enter the commands through the command line, and the same effect is achieved.

Finding unexpected storage overwrite errors in C

During program run time, some storage might unexpectedly change its value and you want to find out when and where this happens. Consider this example where function `set_i` changes more than the caller expects it to change.

```
struct s { int i; int j;};
struct s a = { 0, 0 };

/* function sets only field i */
void set_i(struct s * p, int k)
{
    p->i = k;
    p->j = k; /* error, it unexpectedly sets field j also */
}
```

```

}
main() {
    set_i(&a,123);
}

```

Find the address of a with the command

```
LIST &(a.j) ;
```

Suppose the result is 0x7042A04. To set a breakpoint that watches for a change in storage values starting at that address for the next 4 bytes, issue the command:

```
AT CHANGE %STORAGE(0x7042A04,4)
```

When the program is run, Debug Tool will halt if the value in this storage changes.

Finding uninitialized storage errors in C

To help find your uninitialized storage errors, run your program with the Language Environment TEST run-time and STORAGE options. In the following example:

```
TEST STORAGE(FD,FB,F9)
```

the first subparameter of STORAGE is the fill byte for storage allocated from the heap. For example, storage allocated through malloc() is filled with the byte 0xFD. If you see this byte repeated through storage, it is likely uninitialized heap storage.

The second subparameter of STORAGE is the fill byte for storage allocated from the heap but then freed. For example, storage freed by calling free() might be filled with the byte 0xFB. If you see this byte repeated through storage, it is likely storage that was allocated on the heap, but has been freed.

The third subparameter of STORAGE is the fill byte for auto storage variables in a new stack frame. If you see this byte repeated through storage, it is likely uninitialized auto storage.

The values chosen in the example are odd and large, to maximize early problem detection. For example, if you attempt to branch to an odd address you will get an exception immediately.

“Example: sample C program for debugging” on page 163

As an example of uninitialized heap storage, run program CALC with the STORAGE run-time option as STORAGE(FD,FB,F9) to the line labeled PUSHPOP2 and issue the command:

```
LIST *ptr ;
```

You will see the byte fill for uninitialized heap storage as the following example shows:

```

LIST * ptr ;
(* ptr).next = 0xFDFDFDFD
(* ptr).i = -33686019

```

Halting before calling a NULL C function

Calling an undefined function or calling a function through a function pointer that points to NULL is a severe error. To halt just before such a call is run, set this breakpoint:

```
AT CALL 0
```

When Debug Tool stops at this breakpoint, you can bypass the CALL by entering the GO BYPASS command. This allows you to continue your debug session without raising a condition.

Chapter 27. Debugging a C++ program in full-screen mode

The descriptions of basic debugging tasks for C++ refer to the following C++ program.

“Example: sample C++ program for debugging”

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 34, “Debugging C and C++ programs,” on page 237

“Halting when certain functions are called in C++” on page 177

“Modifying the value of a C++ variable” on page 177

“Halting on a line in C++ only if a condition is true” on page 178

“Viewing and modifying data members of the this pointer in C++” on page 179

“Debugging C++ when only a few parts are compiled with TEST” on page 179

“Capturing C++ output to stdout” on page 180

“Calling a C++ function from Debug Tool” on page 180

“Displaying raw storage in C++” on page 180

“Debugging a C++ DLL” on page 180

“Getting a function traceback in C++” on page 181

“Tracing the run-time path for C++ code compiled with TEST” on page 181

“Finding unexpected storage overwrite errors in C++” on page 182

“Finding uninitialized storage errors in C++” on page 182

“Halting before calling a NULL C++ function” on page 183

Example: sample C++ program for debugging

The program below is used in various topics to demonstrate debugging tasks.

This program is a simple calculator that reads its input from a character buffer. If integers are read, they are pushed on a stack. If one of the operators (+ - * /) is read, the top two elements are popped off the stack, the operation is performed on them, and the result is pushed on the stack. The = operator writes out the value of the top element of the stack to a buffer.

CALC.HPP

```
/*----- FILE CALC.HPP -----*/
/*
/* Header file for CALC.CPP PUSHPOP.CPP READTKN.CPP
/* a simple calculator
/*-----*/
typedef enum toks {
    T_INTEGER,
    T_PLUS,
    T_TIMES,
    T_MINUS,
    T_DIVIDE,
    T_EQUALS,
    T_STOP
} Token;
extern "C" Token read_token(char buf[]);
class IntLink {
private:
    int i;
    IntLink * next;
```

```

public:
    IntLink();
    ~IntLink();
    int get_i();
    void set_i(int j);
    IntLink * get_next();
    void set_next(IntLink * d);
};
class IntStack {
private:
    IntLink * top;
public:
    IntStack();
    ~IntStack();
    void push(int);
    int pop();
};

```

CALC.CPP

```

/*----- FILE CALC.CPP -----*/
/*
/* A simple calculator that does operations on integers that
/* are pushed and popped on a stack
/*-----*/
#include <stdio.h>
#include <stdlib.h>
#include "calc.hpp"
IntStack stack;
int main()
{
    Token tok;
    char word[100];
    char buf_out[100];
    int num, num2;
    for(;;)
    {
        tok=read_token(word);
        switch(tok)
        {
            case T_STOP:
                break;
            case T_INTEGER:
                num = atoi(word);
                stack.push(num);    /* CALC1 statement */
                break;
            case T_PLUS:
                stack.push(stack.pop()+stack.pop());
                break;
            case T_MINUS:
                num = stack.pop();
                stack.push(num-stack.pop());
                break;
            case T_TIMES:
                stack.push(stack.pop()*stack.pop() );
                break;
            case T_DIVIDE:
                num2 = stack.pop();
                num = stack.pop();
                stack.push(num/num2);    /* CALC2 statement */
                break;
            case T_EQUALS:
                num = stack.pop();
                sprintf(buf_out,"= %d ",num);
                stack.push(num);
                break;
        }
    }
}

```

```

        if (tok==T_STOP)
            break;
    }
    return 0;
}

```

PUSHPOP.CPP

```

/*----- FILE: PUSHPOP.CPP -----*/
/*
/* Push and pop functions for a stack of integers
/*-----*/
#include <stdio.h>
#include <stdlib.h>
#include "calc.hpp"
/*-----*/
/* input:  num - value to push on the stack
/* action: get a link to hold the pushed value, push link on stack
/*-----*/
void IntStack::push(int num) {
    IntLink * ptr;
    ptr = new IntLink;
    ptr->set_i(num);
    ptr->set_next(top);
    top = ptr;
}
/*-----*/
/* return: int value popped from stack (0 if stack is empty)
/* action: pops top element from stack and get return value from it
/*-----*/
int IntStack::pop() {
    IntLink * ptr;
    int num;
    ptr = top;
    num = ptr->get_i();
    top = ptr->get_next();
    delete ptr;
    return num;
}
IntStack::IntStack() {
    top = 0;
}
IntStack::~IntStack() {
    while(top)
        pop();
}
IntLink::IntLink() { /* constructor leaves elements unassigned */
}
IntLink::~IntLink() {
}
void IntLink::set_i(int j) {
    i = j;
}
int IntLink::get_i() {
    return i;
}
void IntLink::set_next(IntLink * p) {
    next = p;
}
IntLink * IntLink::get_next() {
    return next;
}
}

```

READTOKN.CPP

```

/*----- FILE READTOKN.CPP -----*/
/*
/* A function to read input and tokenize it for a simple calculator
/*-----*/

```

```

/*-----*/
#include <ctype.h>
#include <stdio.h>
#include "calc.hpp"
/*-----*/
/* action: get next input char, update index for next call */
/* return: next input char */
/*-----*/
static char nextchar(void)
{
    /*    input  action
     *    ----  -
     *    2      push 2 on stack
     *    18     push 18
     *    +      pop 2, pop 18, add, push result (20)
     *    =      output value on the top of the stack (20)
     *    5      push 5
     *    /      pop 5, pop 20, divide, push result (4)
     *    =      output value on the top of the stack (4)
     */
    char * buf_in = "2 18 + = 5 / = ";
    static int index; /* starts at 0 */
    char ret;
    ret = buf_in[index];
    ++index;
    return ret;
}
/*-----*/
/* output: buf - null terminated token */
/* return: token type */
/* action: reads chars through nextchar() and tokenizes them */
/*-----*/
extern "C"
Token read_token(char buf[])
{
    int i;
    char c;
    /* skip leading white space */
    for( c=nextchar();
        isspace(c);
        c=nextchar())
        ;
    buf[0] = c; /* get ready to return single char e.g. "+" */
    buf[1] = 0;
    switch(c)
    {
        case '+' : return T_PLUS;
        case '-' : return T_MINUS;
        case '*' : return T_TIMES;
        case '/' : return T_DIVIDE;
        case '=' : return T_EQUALS;
        default:
            i = 0;
            while (isdigit(c)) {
                buf[i++] = c;
                c = nextchar();
            }
            buf[i] = 0;
            if (i==0)
                return T_STOP;
            else
                return T_INTEGER;
    }
}

```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 27, “Debugging a C++ program in full-screen mode,” on page 173

Halting when certain functions are called in C++

You need to include the C++ signature along with the function name to set an AT ENTRY or AT CALL breakpoint for a C++ function.

“Example: sample C++ program for debugging” on page 173

To facilitate entering the breakpoint, you can display PUSHPOP.CPP in the Source window by typing over the name of the file on the top line of the Source window. This makes PUSHPOP.CPP your currently qualified program. You can then issue the command:

```
LIST NAMES
```

which displays the names of all the blocks and variables for the currently qualified program. Debug Tool displays information similar to the following in the Log window:

```
There are no session names.  
The following names are known in block CALC ::> "USERID.MFISTART.CPP(PUSHPOP)"  
IntStack::~IntStack()  
IntStack::IntStack()  
IntLink::get_i()  
IntLink::get_next()  
IntLink::~IntLink()  
IntLink::set_i(int)  
IntLink::set_next(IntLink*)  
IntLink::IntLink()
```

Now you can save some keystrokes by inserting the command next to the block name.

To halt just before `IntStack::push(int)` is called, insert AT CALL next to the function signature and, by pressing Enter, the entire command is placed on the command line. Now, with AT CALL `IntStack::push(int)` on the command line, you can enter the command:

```
AT CALL IntStack::push(int)
```

To halt just after `IntStack::push(int)` is called, issue the command:

```
AT ENTRY IntStack::push(int) ;
```

in the same way as the AT CALL command.

To be able to halt, the file with the calling code must be compiled with the TEST compiler option.

Modifying the value of a C++ variable

To list the contents of a single variable, move the cursor to the variable name and press PF4 (LIST). The value is displayed in the Log window. This is equivalent to entering LIST TITLED *variable* on the command line.

“Example: sample C++ program for debugging” on page 173

Run the CALC program and step into the first call of function `IntStack::push(int)` until just after the `IntLink` has been allocated. Enter the Debug Tool command:

```
LIST TITLED num
```

Debug Tool displays the following in the Log window:

```
LIST TITLED num;  
num = 2
```

To modify the value of `num` to 22, type over the `num = 2` line with `num = 22`, press Enter to put it on the command line, and press Enter again to issue the command.

You can enter most C++ expressions on the command line.

To view the attributes of variable `ptr` in `IntStack::push(int)`, issue the Debug Tool command:

```
DESCRIBE ATTRIBUTES *ptr;
```

The result in the Log window is:

```
ATTRIBUTES for * ptr  
Its address is 0BA25EB8 and its length is 8  
class IntLink  
    signed int i  
    struct IntLink *next
```

So for most classes, structures, and unions, this can act as a browser.

You can list all the values of the data members of the class object pointed to by `ptr` with the command:

```
LIST *ptr ;
```

with results in the Log window similar to:

```
LIST * ptr ; * ptr.i = 0 * ptr.next = 0x00000000
```

You can change the value of data member of a class object by issuing the assignment as a command, as in this example:

```
(* ptr).i = 33 ;
```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using C and C++ variables with Debug Tool” on page 238

Halting on a line in C++ only if a condition is true

Often a particular part of your program works fine for the first few thousand times, but fails under certain conditions. You don’t want to set a simple line breakpoint because you will have to keep entering G0.

“Example: sample C++ program for debugging” on page 173

For example, in `main` you want to stop in `T_DIVIDE` only if the divisor is 0 (before the exception occurs). Set the breakpoint like this:

```
AT 40 { if(num2 != 0) G0; }
```

Line 40 is the statement labeled **CALLC2** . The command causes Debug Tool to stop at line 40. If the value of num is not 0, the program will continue. Debug Tool stops on line 40 only if num2 is 0.

Viewing and modifying data members of the this pointer in C++

If you step into a class method, for example, one for class IntLink, the command:

```
LIST TITLED ;
```

responds with a list that includes this. With the command:

```
DESCRIBE ATTRIBUTES *this ;
```

you will see the types of the data elements pointed to by the this pointer. With the command:

```
LIST *this ;
```

you will list the data member of the object pointed to and see something like:

```
LIST * this ;
(* this).i = 4
(* this).next = 0x0
```

in the Log window. To modify element i, enter either the command:

```
i = 2001;
```

or, if you have ambiguity (for example, you also have an auto variable named i), enter:

```
(* this).i = 2001 ;
```

Debugging C++ when only a few parts are compiled with TEST

“Example: sample C++ program for debugging” on page 173

Suppose you want to set a breakpoint at entry to function IntStack::push(int) in the file PUSHPOP.CPP. PUSHPOP.CPP has been compiled with TEST but the other files have not. Debug Tool comes up with an empty Source window. To display the compile units, enter the command:

```
LIST NAMES CUS
```

The LIST NAMES CUS command displays a list of all the compile units that are known to Debug Tool.

Depending on the compiler you are using, or if USERID.MFISTART.CPP(PUSHPOP) is fetched later on by the application, this compile unit might or might not be known to Debug Tool, and the PDS member PUSHPOP might or might not be displayed. If it is displayed, enter:

```
SET QUALIFY CU "USERID.MFISTART.CPP(PUSHPOP)"
AT ENTRY IntStack::push(int) ;
GO ;
```

or

```
AT ENTRY "USERID.MFISTART.CPP(PUSHPOP)":>push
GO
```

If it is not displayed, you need to set an appearance breakpoint as follows:

```
AT APPEARANCE "USERID.MFISTART.CPP(PUSHPOP)" ;  
GO ;
```

You can also combine the breakpoints as follows:

```
AT APPEARANCE "USERID.MFISTART.CPP(PUSHPOP)" AT ENTRY push; GO;
```

The only purpose of this appearance breakpoint is to gain control the first time a function in the PUSHPOP compile unit is run. When that happens you can, for example, set a breakpoint at entry to `IntStack::push(int)` as follows:

```
AT ENTRY IntStack::push(int) ;
```

Capturing C++ output to stdout

To redirect stdout to the Log window, issue the following command:

```
SET INTERCEPT ON FILE stdout ;
```

With this SET command, you will not only capture stdout from your program, but also from interactive function calls. For example, you can interactively use `cout` on the command line to display a null terminated string by entering:

```
cout << sptr ;
```

You might find this easier than using LIST STORAGE.

For CICS only, SET INTERCEPT is not supported.

Calling a C++ function from Debug Tool

You can start a library function (such as `strlen`) or one of the programs functions interactively by calling it on the command line. The same is true of C linkage functions such as `read_token`. You cannot call C++ linkage functions interactively.

“Example: sample C++ program for debugging” on page 173

In the example below, we call `read_token` interactively.

```
AT CALL read_token;  
GO;  
read_token(word);
```

The calculator produces different results than before because of the additional token removed from input.

Displaying raw storage in C++

A `char *` variable `ptr` can point to a piece of storage containing printable characters. To display the first 20 characters, enter;

```
LIST STORAGE(*ptr,20)
```

If the string is null terminated, you can also use an interactive function call on the command line as shown in this example:

```
puts(ptr) ;
```

Debugging a C++ DLL

“Example: sample C++ program for debugging” on page 173

Build PUSHPOP.CPP as a DLL, exporting IntStack::push(int) and IntStack::pop(). Build CALC.CPP and READTKN.CPP as the program that imports IntStack::push(int) and IntStack::pop() from the DLL named PUSHPOP. When the application CALC starts, the DLL PUSHPOP is not known to Debug Tool. Use the AT APPEARANCE breakpoint, as shown in the following example, to gain control in the DLL the first time code in that compile unit appears.

```
AT APPEARANCE "USERID.MFISTART.CPP(PUSHPOP)" ;
GO ;
```

The only purpose of this appearance breakpoint is to gain control the first time a function in the PUSHPOP compile unit is run. When this happens, you can set breakpoints in PUSHPOP.

Getting a function traceback in C++

Often when you get close to a programming error, you want to know how you got into that situation, especially what the traceback of calling functions is. To get this information, issue the command:

```
LIST CALLS ;
```

For example, if you run the CALC example with the following commands:

```
AT ENTRY read_token ;
GO ;
LIST CALLS ;
```

the Log window contains something like:

```
At ENTRY in C function "USERID.MFISTART.CPP(READTKN)" :> read_token.
From LINE 18 in C function "USERID.MFISTART.CPP(CALC)" :> main :> %BLOCK2.
```

which shows the traceback of callers.

Tracing the run-time path for C++ code compiled with TEST

To trace a program showing the entry and exit of that program without requiring any changes to it, place the following Debug Tool commands, shown in the example below, in a file and USE them when Debug Tool initially displays your program. Assume you have a data set that contains USERID.DTUSE(TRACE) and contains the following Debug Tool commands:

```
int indent;
indent = 0;
SET INTERCEPT ON FILE stdout;
AT ENTRY * { \
    ++indent; \
    if (indent < 0) indent = 0; \
    printf("%*.s>%s\n", indent, " ", %block); \
    GO; \
}
AT EXIT * {\
    if (indent < 0) indent = 0; \
    printf("%*.s<%s\n", indent, " ", %block); \
    --indent; \
    GO; \
}
```

You can use this file as the source of commands to Debug Tool by entering the following command:

```
USE USERID.DTUSE(TRACE)
```

The trace of running the program listed below after executing the USE file is displayed in the Log window:

```
int foo(int i, int j) {
    return i+j;
}
int main(void) {
    return foo(1,2);
}
```

The following trace in the Log window is displayed after running the sample program, using the USE file as a source of input for Debug Tool commands:

```
>main
>foo(int,int)
<foo(int,int)
<main
```

If you do not want to create the USE file, you can enter the commands through the command line, and the same effect will be achieved.

Finding unexpected storage overwrite errors in C++

During program run time, some storage might unexpectedly change its value and you would like to find out when and where this happened. Consider this simple example where function `set_i` changes more than the caller expects it to change.

```
struct s { int i; int j;};
struct s a = { 0, 0 };

/* function sets only field i */
void set_i(struct s * p, int k)
{
    p->i = k;
    p->j = k; /* error, it unexpectedly sets field j also */
}
main() {
    set_i(&a,123);
}
```

Find the address of `a` with the command:

```
LIST &(a.j) ;
```

Suppose the result is `0x7042A04`. To set a breakpoint that watches for a change in storage values, starting at that address for the next 4 bytes, issue the command:

```
AT CHANGE %STORAGE(0x7042A04,4)
```

When the program is run, Debug Tool will halt if the value in this storage changes.

Finding uninitialized storage errors in C++

To help find your uninitialized storage errors, run your program with the Language Environment TEST run-time and STORAGE options. In the following example:

```
TEST STORAGE(FD,FB,F9)
```

the first subparameter of STORAGE is the fill byte for storage allocated from the heap. For example, storage allocated through operator `new` is filled with the byte `0xFD`. If you see this byte repeated throughout storage, it is likely uninitialized heap storage.

The second subparameter of STORAGE is the fill byte for storage allocated from the heap but then freed. For example, storage freed by the operator delete might be filled with the byte 0xFB. If you see this byte repeated throughout storage, it is likely storage that was allocated on the heap, but has been freed.

The third subparameter of STORAGE is the fill byte for auto storage variables in a new stack frame. If you see this byte repeated throughout storage, it is likely that it is uninitialized auto storage.

The values chosen in the example are odd and large, to maximize early problem detection. For example, if you attempt to branch to an odd address, you will get an exception immediately.

As an example of uninitialized heap storage, run program CALC, with the STORAGE run-time option as STORAGE(FD,FB,F9), to the line labeled PUSHPOP2 and issue the command:

```
LIST *ptr ;
```

You will see the byte fill for uninitialized heap storage as the following example shows:

```
LIST * ptr ;  
(* ptr).next = 0xFDFDFDFD  
(* ptr).i = -33686019
```

Refer to the following sections for more information related to the material discussed in this section.

Related references

z/OS Language Environment Programming Guide

Halting before calling a NULL C++ function

Calling an undefined function or calling a function through a function pointer that points to NULL is a severe error. To halt just before such a call is run, set this breakpoint:

```
AT CALL 0
```

When Debug Tool stops at this breakpoint, you can bypass the call by entering the GO BYPASS command. This command allows you to continue your debug session without raising a condition.

Chapter 28. Debugging an assembler program in full-screen mode

The descriptions of basic debugging tasks for assembler refer to the following assembler program.

“Example: sample assembler program for debugging”

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 35, “Debugging an assembler program,” on page 261

“Defining a compilation unit as assembler and loading debug data” on page 188

“Deferred LDDs” on page 189

“Halting when certain assembler routines are called” on page 190

“Displaying and modifying the value of assembler variables or storage” on page 190

“Halting on a line in assembler only if a condition is true” on page 191

“Getting an assembler routine traceback” on page 191

“Finding unexpected storage overwrite errors in assembler” on page 192

Example: sample assembler program for debugging

The program below is used in various topics to demonstrate debugging tasks.

To run this sample program, do the following steps:

1. Verify that the debug file for this assembler program is located in the SUBXMP and DISPARM members of the *yourid*.EQALANGX data set.
2. Start Debug Tool.
3. To load the information in the debug file, enter the following commands:
LDD (SUBXMP,DISPARM)

This program is a small example of an assembler main routine (SUBXMP) that calls an assembler subroutine (DISPARM).

Load module: XMPLOAD

SUBXMP.ASM

```
*****
*                                                                 *
*  NAME: SUBXMP                                                  *
*                                                                 *
*      A simple main assembler routine that brings up           *
*      Language Environment, calls a subroutine, and             *
*      returns with a return code of 0.                          *
*                                                                 *
*****
SUBXMP  CEEENTRY PPA=XMPPPA,AUTO=WORKSIZE
        USING WORKAREA,R13
* Invoke CEEMOUT to issue the greeting message
        CALL  CEEMOUT,(HELLOMSG,DEST,FBCODE),VL,MF=(E,CALLMOUT)
* No plist to DISPARM, so zero R1. Then call it.
        SLR   R0,R0
```



```

        ST    R0,COUNTER
        LA    R0,HELLOMSG
        SR    R01,R01 ssue a message
        CALL  DISPARM
* Invoke CEEMOUT to issue the farewell message
        CALL  CEEMOUT,(BYEMSG,DEST,FBCODE),VL,MF=(E,CEEMOUT)
* Terminate Language Environment and return to the caller
        CEETERM RC=0

*      CONSTANTS
HELLOMSG DC    Y(HELLOEND-HELLOSTR)
HELLOSTR DC    C'Hello from the sub example.'
HELLOEND EQU    *

BYEMSG   DC    Y(BYEEND-BYESTART)
BYESTART DC    C'Terminating the sub example.'
BYEEND   EQU    *
DEST     DC    F'2'                Destination is the LE message file
COUNTER  DC    F'-1'

XMPPPA   CEEPPA ,                  Constants describing the code block
*        The Workarea and DSA
WORKAREA DSECT
        ORG    **CEEDSASZ          Leave space for the DSA fixed part
CALLMOUT CALL  ,(,,),VL,MF=L       3-argument parameter list
FBCODE   DS    3F                  Space for a 12-byte feedback code
        DS    0D
WORKSIZE EQU    *-WORKAREA
        PRINT NOGEN
        CEEDSA ,                  Mapping of the dynamic save area
        CEECAA ,                  Mapping of the common anchor area
R0        EQU    0
R01       EQU    1
R13       EQU    13
END       SUBXMP                    Nominate SUBXMP as the entry point

```

DISPARM.ASM

```

*****
*
*      NAME:  DISPARM
*
*      Shows an assembler subroutine that displays inbound
*      parameters and returns.
*
*****
DISPARM  CEEENTRY PPA=PARMPPA,AUTO=WORKSIZE,MAIN=NO
        USING WORKAREA,R13
* Invoke CEE3PRM to retrieve the command parameters for us
        SLR    R0,R0
        ST     R0,COUNTER
        CALL   CEE3PRM,(CHARPARM,FBCODE),VL,MF=(E,CALL3PRM)
* Check the feedback code from CEE3PRM to see if everything worked.
        CLC    FBCODE(8),CEE000
        BE     GOT_PARM
* Invoke CEEMOUT to issue the error message for us
        CALL   CEEMOUT,(BADFBC,DEST,FBCODE),VL,MF=(E,CALLMOUT)
        B      GO_HOME              Time to go...
GOT_PARM DS    0H
* See if the parm string is blank.
        LA     R1,1
SAVECTR  ST     R1,COUNTER
        CL     R1,=F'5'
        BH     LOOPEND
        LA     R1,1(,R1)
        B      SAVECTR
LOOPEND  DS     0H

```

```

        CLC    CHARPDM(80),=CL80' '    Is the parm empty?
        BNE    DISPLAY_PARM            No. Print it out.
* Invoke CEEMOUT to issue the error message for us
        CALL   CEEMOUT,(NOPARM,DEST,FBCODE),VL,MF=(E,CALLMOUT)
        B      GO_TEST                Time to go....

DISPLAY_PARM DS 0H
* Set up the plist to CEEMOUT to display the parm.
        LA     R0,2
        ST     R0,COUNTER
        LA     R02,80                  Get the size of the string
        STH    R02,BUFFSIZE            Save it for the len-prefixed string
* Invoke CEEMOUT to display the parm string for us
        CALL   CEEMOUT,(BUFFSIZE,DEST,FBCODE),VL,MF=(E,CALLMOUT)
*
        AMODE Testing
GO_TEST DS 0H
        L      R15,INAMODE24@
        BSM    R14,R15
InAMode24 Equ *
        LA     R1,DEST
        O      R1,=X'FF000000'
        L      R15,0(,R1)
        LA     R15,2(,R15)
        ST     R15,0(,R1)
        L      R15,INAMODE31@
        BSM    R14,R15
InAMode31 Equ *
* Return to the caller
GO_HOME DS 0H
        LA     R0,3
        ST     R0,COUNTER
        CEETERM RC=0

*
CONSTANTS
DEST DC F'2'                          Destination is the LE message file
CEE000 DS 3F'0'                        Success feedback code
InAMode24@ DC A(InAMode24)
InAMode31@ DC A(InAMode31+X'80000000')
BADFBC DC Y(BADFBEND-BADFBSTR)
BADFBSTR DC C'Feedback code from CEE3PRM was nonzero.'
BADFBEND EQU *
NOPARM DC Y(NOPRMEND-NOPRMSTR)
NOPRMSTR DC C'No user parm was passed to the application.'
NOPRMEND EQU *
PARMPPA CEEPPA ,                      Constants describing the code block
* =====
WORKAREA DSECT
        ORG    **CEEDSASZ              Leave space for the DSA fixed part
CALL3PRM CALL ,(,),VL,MF=L             2-argument parameter list
CALLMOUT CALL ,(,),VL,MF=L            3-argument parameter list
FBCODE DS 3F                          Space for a 12-byte feedback code
COUNTER DS F
BUFFSIZE DS H                         Halfword prefix for following string
CHARPDM DS CL255                      80-byte buffer
        DS 0D
WORKSIZE EQU *-WORKAREA
        PRINT NOGEN
        CEEDSA ,                      Mapping of the dynamic save area
        CEECAA ,                      Mapping of the common anchor area
MYDATA DSECT ,
MYF DS F
R0 EQU 0
R1 EQU 1
R2 EQU 2
R3 EQU 3
R4 EQU 4
R5 EQU 5

```

R6	EQU	6
R7	EQU	7
R8	EQU	8
R9	EQU	9
R10	EQU	10
R11	EQU	11
R12	EQU	12
R13	EQU	13
R14	EQU	14
R15	EQU	15
R02	EQU	2
	END	

Defining a compilation unit as assembler and loading debug data

Before you can debug an assembler program, you must define the compilation unit (CU) as an assembler CU and load the debug data for the CU. This can only be done for a CU that is currently known to Debug Tool as a disassembly CU.

You use the `LOADDEBUGDATA` command (abbreviated as `LDD`) to define a disassembly CU as an assembler CU and to cause the debug data for this CU to be loaded. When you run the `LDD` command, you can specify either a single CU name or a list of CU names enclosed in parenthesis. Each of the names specified must be either:

- the name of a disassembly CU that is currently known to Debug Tool
- a name that does not match the name of a CU currently known to Debug Tool

When the CU name is currently known to Debug Tool, the CU is immediately marked as an assembler CU and an attempt is made to load the debug data as follows:

- If your assembler debug data is in a partitioned data set where the high-level qualifier is the current user ID, the low-level qualifier is `EQALANGX`, and the member name is the same as the name of the CU that you want to debug no other action is necessary
- If your assembler debug data is in a different partitioned data set than `userid.EQALANGX` but the member name is the same as the name of the CU that you want to debug, enter the following command before or after you enter the `LDD` command: `SET DEFAULT LISTINGS`
- If your assembler debug data is in a sequential data set or is a member of a partitioned data set but the member name is different from the CU name, enter the following command before or after the `LDD`: `SET SOURCE`

When the CU name specified on the `LDD` command is not currently known to Debug Tool, a message is issued and the `LDD` command is deferred until a CU by that name becomes known (appears). At that time, the CU is automatically created as an assembler CU and an attempt is made to load the debug data using the default data set name or the current `SET DEFAULT LISTINGS` specification.

After you have entered an `LDD` command for a CU, you cannot view the CU as a disassembly CU.

If Debug Tool cannot find the associated assembler debug data after you have entered an `LDD` command, the CU is an assembler CU rather than a disassembly CU. You cannot enter another `LDD` command for this CU. However, you can enter a `SET DEFAULT LISTING` command or a `SET SOURCE` command to cause the associated debug data to be loaded from a different data set.

Deferred LDDs

As described in the previous section, you can use the LDD command to identify a CU as an assembler CU before the CU has become known to Debug Tool. This is known as a deferred LDD. In this case, whenever the CU appears, it is immediately marked as an assembler CU and an attempt is made to load the debug data from the default data set name or from the data set currently specified by SET DEFAULT LISTINGS.

If the debug data cannot be found in this way, you must use the SET SOURCE or SET DEFAULT LISTINGS command after the CU appears to cause the debug data to be loaded from the correct dataset. You can do this using a command such as:

```
AT APPEARANCE mycu SET SOURCE (mycu) hlq.qual1.dsn
```

Alternatively, you might wait until you have stopped for some other reason after "mycu" has appeared and then use the SET SOURCE or SET DEFAULT LISTING commands to direct Debug Tool to the proper data set.

Re-appearance of an assembler CU

If a CU from which valid assembler debug data has been loaded goes away and then reappears (e.g., the load module is deleted and then reloaded), the CU is immediately marked as an assembler CU and the debug data is reloaded from the data set from which it was successfully loaded originally.

You do not need to (and cannot) issue another LDD for that CU because it is already known as an assembler CU and the debug data has already been loaded.

Multiple compilation units in a single assembly

Debug Tool treats each assembler CSECT as a separate compilation unit (CU). If your assembler source contains more than one CSECT, the EQALANGX file, which you create by running the EQALANGX program, contains debug information for all CSECTs. Debug Tool, however, locates debug information as if each CU (CSECT) were in separate EQALANGX files.

For example, you have an assembly that generates two CSECTs: MYPROG and MYPROGA. The debug information for both of these CSECTs is in the data set yourid.EQALANGX(MYPROG). If you enter the command LDD MYPROG, Debug Tool finds and loads the debug information for both MYPROG and MYPROGA. However, because you specified only MYPROG on the LDD command, Debug Tool uses only the debug information for MYPROG. Then, if you enter the command LDD MYPROGA, Debug Tool does the following steps:

1. If you entered a SET SOURCE command before entering the LDD MYPROG command, Debug Tool loads the debug data from the data set that you specified with the SET SOURCE command.
2. If you did not enter the SET SOURCE command or if Debug Tool did not find debug information in step 1, Debug Tool searches through all previously loaded debug information. If Debug Tool finds a name and CSECT length that matches the name and CSECT length of MYPROGA, Debug Tool uses this debug information.

To instruct Debug Tool to use the debug information for MYPROGA that is located in yourid.EQALANGX(MYPROGA), enter the SET SOURCE command, either before or after

you enter the LDD MYPROGA command. The SET SOURCE command instructs Debug Tool to associate the data set name yourid.EQALANGX(MYPROGA) with the CU MYPROGA and to ignore the previously loaded debug information from MYPROG.

The following set of commands instruct Debug Tool to load debug information for MYPROG and MYPROGA from the MYPROG member of the EQALANGX data set:

```
LDD MYPROG ;  
SET SOURCE ON (MYPROGA) myuserid.EQALANGX(MYPROG) ;  
LDD MYPROGA ;
```

Halting when certain assembler routines are called

“Example: sample assembler program for debugging” on page 185

To halt after the DISPARM routine is called, enter the command:

```
AT ENTRY DISPARM
```

The AT CALL command is not supported for assembler routines. Do not use the AT CALL command to stop Debug Tool when an assembler routine is called.

If you have many breakpoints set in your program, you can issue the command:

```
QUERY LOCATION
```

to indicate where in your program execution has been interrupted. The Debug Tool Log window displays something similar to:

```
QUERY LOCATION
```

You are executing commands in the ENTRY XMPLOAD ::> DISPARM breakpoint.

The program is currently entering block XMPLOAD ::> DISPARM.

Displaying and modifying the value of assembler variables or storage

To list the contents of a single variable, move the cursor to an occurrence of the variable name in the Source window and press PF4 (LIST). The value is displayed in the Log window. This is equivalent to entering `LIST variable` on the command line.

For example, run the SUBXMP program to the statement labeled **CALL1** by entering `AT 70 ; G0 ;` on the Debug Tool command line. Scroll up until you see line 67. Move the cursor over COUNTER and press PF4 (LIST). The following appears in the Log window:

```
LIST ( COUNTER )  
COUNTER = 0
```

To modify the value of COUNTER to 1, type over the `COUNTER = 0` line with `COUNTER = 1`, press Enter to put it on the command line, and press Enter again to issue the command.

To list the contents of the 16 bytes of storage 2 bytes past the address contained in register R0, type the command `LIST STORAGE(R0->+2,16)` on the command line and press Enter. The contents of the specified storage are displayed in the Log window.

```
LIST STORAGE( R0 -> + 2 , 16 )  
000C321E C8859393 96408699 969440A3 888540A2 *Hello from the s*
```

To modify the first two bytes of this storage to X'C182', type the command R0->+2 <2> = X'C182'; on the command line and press Enter to issue the command.

Now step into the call to DISPARM by pressing PF2 (STEP) and step until the line labeled CALL2 is reached. To view the attributes of variable COUNTER, issue the Debug Tool command:

```
DESCRIBE ATTRIBUTES COUNTER
```

The result in the Log window is:

```
ATTRIBUTES for COUNTER
  Its address is 1B0E2150 and its length is 4
  DS F
```

Converting a hexadecimal address to a symbolic address

While you debug an assembler or disassembly program, you might want to determine the symbolic address represented by a hexadecimal address. You can do this by using the LIST command with the %WHERE built-in function. For example, the following command returns a string indicating the symbolic location of X'1BC5C':

```
LIST %WHERE(X'1BC5C')
```

After you enter the command, Debug Tool displays the following result:

```
PROG1+X'12C'
```

The result indicates that the address X'1BC5C' corresponds to offset X'12C' within CSECT PROG1.

Halting on a line in assembler only if a condition is true

Often a particular part of your program works fine for the first few thousand times, but it fails under certain conditions. Setting a line breakpoint is inefficient because you will have to repeatedly enter the GO command.

“Example: sample assembler program for debugging” on page 185

In the DISPARM program, to stop Debug Tool when the COUNTER variable is set to 3, enter the following command:

```
AT 78 DO; IF COUNTER ^= 3 THEN GO; END;
```

Line 78 is the line labeled **BUMPCTR**. The command causes Debug Tool to stop at line 78. If the value of COUNTER is not 3, the program continues. The command causes Debug Tool to stop on line 78 only if the value of COUNTER is 3.

Getting an assembler routine traceback

Often when you get close to a programming error, you want to know what sequence of calls lead you to the programming error. This sequence is called traceback or traceback of callers. To get the traceback information, enter the following command:

```
LIST CALLS
```

“Example: sample assembler program for debugging” on page 185

For example, if you run the SUBXMP example with the following commands, the Log window displays the traceback of callers:

```
AT ENTRY DISPARM
GO
LIST CALLS
```

The Log window displays information similar to the following:

```
At ENTRY IN Assembler routine XMPLOAD ::> DISPARM.
From LINE 76.1 IN Assembler routine XMPLOAD ::> SUBXMP.
```

Finding unexpected storage overwrite errors in assembler

While your program is running, some storage might unexpectedly change its value and you want to find out when and where this happened. Consider the following example, where the program finds a value unexpectedly modified:

```
L R0,X'24'(R3)
```

To find the address of the operand being loaded, enter the following command:

```
LIST R3->+X'24'
```

Suppose the result is X'00521D42'. To set a breakpoint that watches for a change in storage values starting at that address and for the next 4 bytes, enter the following command:

```
AT CHANGE %STORAGE(X'00521D42',4)
```

When the program runs, Debug Tool stops if the value in this storage changes.

Chapter 29. Customizing your full-screen session

You have several options for customizing your session. For example, you can resize and rearrange windows, close selected windows, change session parameters, and change session panel colors. This section explains how to customize your session using these options.

The window acted upon as you customize your session is determined by one of several factors. If you specify a window name (for example, WINDOW OPEN MONITOR to open the Monitor window), that window is acted upon. If the command is cursor-oriented, such as the WINDOW SIZE command, the window containing the cursor is acted upon. If you do not specify a window name and the cursor is not in any of the windows, the window acted upon is determined by the setting of *Default window* under the Profile Settings panel.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 22, "Using full-screen mode: overview," on page 107

Chapter 29, "Customizing your full-screen session"

"Defining PF keys"

"Defining a symbol for commands or other strings" on page 194

"Customizing the layout of windows on the session panel" on page 194

"Customizing session panel colors" on page 196

"Customizing profile settings" on page 197

"Saving customized settings in a preferences files" on page 199

Defining PF keys

To define your PF keys, use the SET PFKEY command. For example, to define the PF8 key as SCROLL DOWN PAGE, enter one of the following commands:

- For PL/I:
SET PF8 'Down' = SCROLL DOWN PAGE ;
- For C and C++:
SET PF8 "Down" = SCROLL DOWN PAGE ;

Use single quotation marks for PL/I, double quotation marks for C and C++. Assembler, COBOL, and disassembly allow the use of single or double quotation marks. The string set apart by the quotation marks (Down in this example) is the label that appears next to PF8 when you SET KEYS ON and your PF key definitions are displayed at the bottom of your screen.

Refer to the following sections for more information related to the material discussed in this section.

Related references

"Initial PF key settings" on page 117

Defining a symbol for commands or other strings

You can define a symbol to represent a long character string. For example, if you have a long command that you do not want to retype several times, you can use the SET EQUATE command to equate the command to a short symbol. Afterwards, Debug Tool treats the symbol as though it were the command. The following examples show various settings for using EQUATEs:

- SET EQUATE info = "abc, def(h+1)"; Sets the symbol info to the string, "abc, def(h+1)". The use of single quotes (', ') or double quotes (" , ") is language dependent.
- CLEAR EQUATE (info); Disassociates the symbol and the string. This example clears info.
- CLEAR EQUATE; If you do not specify what symbol to clear, all symbols created by SET EQUATE are cleared.

If a symbol created by a SET EQUATE command is the same as a keyword or keyword abbreviation in an HLL, the symbol takes precedence. If the symbol is already defined, the new definition replaces the old. Operands of certain commands are for environments other than the standard Debug Tool environment, and are not scanned for symbol substitution.

Customizing the layout of windows on the session panel

To change the relative layout of the Source, Monitor, and Log windows, use the PANEL LAYOUT command (the PANEL keyword is optional).

The PANEL LAYOUT command displays the panel below, showing the six possible window layouts.

Window Layout Selection Panel

Command ==>

1

1

M
S
L

2

2

-	-
-	-

3

3

-	
-	-

4

4

-	-	-
---	---	---

5

5

-	-
-	-

6

6

-	-
-	-

Legend:

L - Log
M - Monitor
S - Source

To reassign the Source, Monitor, and Log windows, type over the current settings or underscores with L, M, or S.

Enter END/QUIT to return with current settings saved.
CANCEL to return without current settings saved.

Initially, the session panel uses the default window layout **1**.

Follow the instructions on the screen, then press the END PF key to save your changes and return to the main session panel in the new layout.

Note: You can choose only one of the six layouts. Also, only one of each type of window can be visible at a time on your session panel. For example, you cannot have two Log windows on a panel.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Opening and closing session panel windows”

“Resizing session panel windows”

“Zooming a window to occupy the whole screen” on page 196

“Saving customized settings in a preferences files” on page 199

Related references

“Debug Tool session panel” on page 107

Opening and closing session panel windows

To close a window, either:

- Type the WINDOW CLOSE command, move the cursor to the window you want to close, then press Enter.

or

- Enter the WINDOW CLOSE LOG, WINDOW CLOSE MONITOR, or WINDOW CLOSE SOURCE command.

When you close a window, the remaining windows occupy the full area of the screen.

To open a window, enter the WINDOW OPEN LOG, WINDOW OPEN MONITOR, or WINDOW OPEN SOURCE command.

The WINDOW CLOSE command can be assigned to a PF key.

If you want to monitor the values of selected variables as they change during your Debug Tool session, the Monitor window must be open. If it is closed, open it as described above. The Monitor window occupies the available space according to your selected window layout.

If at any time during your session you open a window and the contents assigned to it are not available, the window is empty.

Resizing session panel windows

To resize windows, type WINDOW SIZE on the command line, move the cursor to where you want the window boundary, then press Enter. The WINDOW keyword is optional.

Rather than using the cursor, you can also explicitly specify the number of rows or columns you want the window to contain (as appropriate for the window layout). For example, to change the Source window from 10 rows deep to 12 rows deep, enter:

```
WINDOW SIZE 12 SOURCE
```

WINDOW SIZE can be assigned to a PF key.

To restore window sizes to their default values for the current window layout, enter the PANEL LAYOUT RESET command.

Zooming a window to occupy the whole screen

To toggle a window to full screen (temporarily not displaying the others), move the cursor into that window and press PF10 (ZOOM). Press PF10 to toggle back.

PF11 (ZOOM LOG) toggles the Log window in the same way, without the cursor needing to be in the Log window.

Customizing session panel colors

You can change the color and highlighting on your session panel to distinguish the fields on the panel. Consider highlighting such areas as the current line in the Source window, the prefix area, and the statement identifiers where breakpoints have been set.

To change the color, intensity, or highlighting of various fields of the session panel on a color terminal, use the PANEL COLORS command. When you issue this command, the panel shown below appears.

Color Selection Panel				
Command ==>				
	Color	Highlight	Intensity	
Title : field headers	TURQ	NONE	HIGH	
output fields	GREEN	NONE	LOW	Valid Color:
Monitor: contents	TURQ	REVERSE	LOW	White Yellow Blue
line numbers	TURQ	REVERSE	LOW	Turq Green Pink Red
Source : listing area	WHITE	REVERSE	LOW	
prefix area	TURQ	REVERSE	LOW	Valid Intensity:
suffix area	YELLOW	REVERSE	LOW	High Low
current line	RED	REVERSE	HIGH	
breakpoints	GREEN	NONE	LOW	Valid Highlight:
Log : program output	TURQ	NONE	HIGH	None Reverse
test input	YELLOW	NONE	LOW	Underline Blink
test output	GREEN	NONE	HIGH	
line numbers	BLUE	REVERSE	HIGH	Color and Highlight
Command line	WHITE	NONE	HIGH	are valid only with
Window headers	GREEN	REVERSE	HIGH	color terminals.
Tofeof delimiter	BLUE	REVERSE	HIGH	
Search target	RED	NONE	HIGH	
Enter : END/QUIT	to return with current settings saved.			
CANCEL	to return without current settings saved.			

Initially, the session panel areas and fields have the default color and attribute values shown above.

The usable color attributes are determined by the type of terminal you are using. If you have a monochrome terminal, you can still use highlighting and intensity attributes to distinguish fields.

To change the color and attribute settings for your Debug Tool session, enter the desired colors or attributes over the existing values of the fields you want to change. The changes you make are saved when you enter QUIT.

You can also change the colors or intensity of selected areas by issuing the equivalent SET COLOR command from the command line. Either specify the fields explicitly, or use the cursor to indicate what you want to change. Changing a color or highlight with the equivalent SET command changes the value on the Color Selection Panel.

Settings remain in effect for the entire debug session.

To preserve any changes you make to the default color fields, specify a file before you begin your session using the ddname inspsafe and the dsname or fileid of your choice. Debug Tool recognizes any file with this ddname as the file where it saves session panel settings for use during subsequent sessions. If you do not allocate this file before your session, Debug Tool begins the next debug session with the default values shown in the panel above.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Saving customized settings in a preferences files” on page 199

Customizing profile settings

The PANEL PROFILE command displays the Profile Settings Panel, which contains profile settings that affect the way Debug Tool runs. This panel is shown below with the IBM-supplied initial settings.

Profile Settings Panel		
Command ==>		
	Current Setting	

Change Test Granularity	STATEMENT	(All,Blk,Line,Path,Stmt)
DBCS characters	NO	(Yes or No)
Default Listing PDS name		
Default scroll amount	PAGE	(Page,Half,Max,Csr,Data,int)
Default window	SOURCE	(Log,Monitor,Source)
Execute commands	YES	(Yes or No)
History	YES	(Yes or No)
History size	100	(nonnegative integer)
Logging	YES	(Yes or No)
Pace of visual trace	2	(steps per second)
Refresh screen	NO	(Yes or No)
Rewrite interval	50	(number of output lines)
Session log size	1000	(number of retained lines)
Show log line numbers	YES	(Yes or No)
Show message ID numbers	NO	(Yes or No)
Show monitor line numbers	YES	(Yes or No)
Show scroll field	YES	(Yes or No)
Show source/listing suffix	YES	(Yes or No)
Show warning messages	YES	(Yes or No)
Test level	ALL	(All,Error,None)
Enter	END/QUIT	to return with current settings saved.
	CANCEL	to return without current settings saved.

You can change the settings either by typing your desired values over them, or by issuing the appropriate SET command at the command line or from within a command file.

The profile parameters, their descriptions, and the equivalent SET commands are as follows:

Change Test Granularity

Specifies the granularity of testing for AT CHANGE. Equivalent to SET CHANGE.

DBCS characters

Controls whether the shift-in or shift-out characters are recognized. Equivalent to SET DBCS.

Default Listing PDS name

If specified, the data set where Debug Tool looks for the source or listing. Equivalent to SET DEFAULT LISTINGS.

Default scroll amount

Specifies the default amount assumed for SCROLL commands where no amount is specified. Equivalent to SET DEFAULT SCROLL.

Default window

Selects the default window acted upon when WINDOW commands are issued with the cursor on the command line. Equivalent to SET DEFAULT WINDOW.

Execute commands

Controls whether commands are executed or just checked for syntax errors. Equivalent to SET EXECUTE.

History

Controls whether a history (an account of each time Debug Tool is entered) is maintained. Equivalent to SET HISTORY.

History size

Controls the size of the Debug Tool history table. Equivalent to SET HISTORY.

Logging

Controls whether a log file is written. Equivalent to SET LOG.

Pace of visual trace

Sets the maximum pace of animated execution. Equivalent to SET PACE.

Refresh screen

Clears the screen before each display. REFRESH is useful when there is another application writing to the screen. Equivalent to SET REFRESH.

Rewrite interval

Defines the number of lines of intercepted output that are written by the application before Debug Tool refreshes the screen. Equivalent to SET REWRITE.

Session log size

The number of session log output lines retained for display. Equivalent to SET LOG.

Show log line numbers

Turns line numbers on or off in the log window. Equivalent to SET LOG NUMBERS.

Show message ID numbers

Controls whether ID numbers are shown in Debug Tool messages. Equivalent to SET MSGID.

Show monitor line numbers

Turns line numbers on or off in the monitor window. Equivalent to SET MONITOR NUMBERS.

Show scroll field

Controls whether the scroll amount field is shown in the display. Equivalent to SET SCROLL DISPLAY.

Show source/listing suffix

Controls whether the frequency suffix column is displayed in the Source window. Equivalent TO SET SUFFIX.

Show warning messages (C and C++ and PL/I only)

Controls whether warning messages are shown or conditions raised when commands contain evaluation errors. Equivalent to SET WARNING.

Test level

Selects the classes of exceptions to cause automatic entry into Debug Tool. Equivalent to SET TEST.

A field indicating scrolling values is shown only if the screen is not large enough to show all the profile parameters at once. This field is not shown in the example panel above.

You can change the settings of these profile parameters at any time during your session. For example, you can increase the delay that occurs between the execution of each statement when you issue the STEP command by modifying the amount specified in the *Pace of visual trace* field at any time during your session.

To modify the profile settings for your session, enter a new value over the old value in the field you want to change. Equivalent SET commands are issued when you QUIT from the panel.

Entering the equivalent SET command changes the value on the Profile Settings panel as well.

To preserve any changes you make to the default profile settings, specify a file before you begin your session using the ddname `inspsafe` and the dsname or fileid of your choice. Debug Tool recognizes any file with this ddname as the file where it saves session panel settings for use during subsequent sessions. All PANEL settings are saved, except the setting for the Listing panel and the following settings:

- COUNTRY
- FREQUENCY
- INTERCEPT
- LOG
- NATIONAL LANGUAGE
- PROGRAMMING LANGUAGE
- QUALIFY
- SOURCE
- TEST

If you do not allocate this file before your session, Debug Tool begins the next debug session with the values shown in the example panel above.

Settings remain in effect for the entire debug session.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Saving customized settings in a preferences files”

Saving customized settings in a preferences files

You can place a set of commands into a data set, called a preferences file, and then indicate that file should be used by providing its name in the `preferences_file` suboption of the TEST run-time string. Debug Tool reads these commands at initialization and sets up the session appropriately.

Below is an example preferences file.

```
SET TEST ERROR;  
SET DEFAULT SCROLL CSR;  
SET HISTORY OFF;  
SET MSGID ON;  
DESCRIBE CUS;
```

Part 5. Debugging your programs by using Debug Tool commands

Chapter 30. Entering Debug Tool commands

Debug Tool commands can be issued in three modes: full-screen, line, and batch. Some Debug Tool commands are valid only in certain modes or programming languages. Unless otherwise noted, Debug Tool commands are valid in all modes, and for all supported languages.

For input typed directly at the terminal, input is free-form, optionally starting in column 1.

To separate multiple commands on a line, use a semicolon (;). This terminating semicolon is optional for a single command, or the last command in a sequence of commands.

For input that comes from a commands file or USE file, all of the Debug Tool commands must be terminated with a semicolon, except for the C block command.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

- “Entering commands on the session panel” on page 114
- “Abbreviating Debug Tool keywords” on page 204
- “Entering multiline commands in full-screen and line mode” on page 205
- “Entering multiline commands in a command file” on page 205
- “Entering multiline commands without continuation” on page 206
- “Using blanks in Debug Tool commands” on page 206
- “Entering comments in Debug Tool commands” on page 206
- “Using constants in Debug Tool commands” on page 207
- “Getting online help for Debug Tool command syntax” on page 207

Related references

Debug Tool for z/OS Reference and Messages

Using uppercase, lowercase, and DBCS in Debug Tool commands

The character set and case vary with the double-byte character set (DBCS) or the current programming language setting in a Debug Tool session.

DBCS

When the DBCS setting is ON, you can specify DBCS characters in the following portions of all the Debug Tool commands:

- Commentary text
- Character data valid in the current programming language
- Symbolic identifiers such as variable names (for COBOL, this includes session variables), entry names, block names, and so forth (if the names contain DBCS characters in the application program).

When the DBCS setting is OFF, double-byte data is not correctly interpreted or displayed. However, if you use the shift-in and shift-out codes as data instead of DBCS indicators, you should issue SET DBCS OFF.

If you are debugging in full-screen mode and your terminal is not DBCS capable, the SET DBCS ON command is not available.

Character case and DBCS in C and C++

For both C and C++, Debug Tool sets the programming language to C. When the current programming language setting is C:

- All keywords and identifiers must be the correct case. Debug Tool does not do conversion to uppercase.
- DBCS characters are allowed only within comments and literals.
- Either trigraphs or the equivalent special characters can be used. Trigraphs are treated as their equivalents at all times. For example, FIND "??<" would find not only "??<" but also "{".
- The vertical bar (|) can be entered for the following C and C++ operations: bitwise or (|), logical or (||), and bitwise assignment or (|=).
- There are alternate code points for the following C and C++ characters: vertical bar (|), left brace ({), right brace (}), left bracket ([), and right bracket (]). Although alternate code points will be accepted as input for the braces and brackets, the primary code points will always be logged.

Character case in COBOL and PL/I

When the current programming language setting is *not* C, commands can generally be either uppercase, lowercase, or mixed. Characters in the range *a* through *z* are automatically converted to uppercase except within comments and quoted literals. Also, in PL/I, only "I" and "<->" can be used as the boolean operators for OR and NOT.

Abbreviating Debug Tool keywords

When you issue the Debug Tool commands, you can truncate most command keywords. You cannot truncate reserved keywords for the different programming languages, system keywords (that is, SYS, SYSTEM, or TSO) or special case keywords such as BEGIN, CALL, COMMENT, COMPUTE, END, FILE (in the SET INTERCEPT and SET LOG commands), GOTO, INPUT, LISTINGS (in the SET DEFAULT LISTINGS command), or USE. In addition, PROCEDURE can only be abbreviated as PROC.

The system keywords, and COMMENT, INPUT, and USE keywords, take precedence over other keywords and identifiers. If one of these keywords is followed by a blank, it is always parsed as the corresponding command. Hence, if you want to assign the value 2 to a variable named TSO and the current programming language setting is C, the "=" must be abutted to the reference, as in "TS0<no space>= 2;" not "TS0<space>= 2;". If you want to define a procedure named USE, you must enter "USE<no space>: procedure;" not "USE<space>:: procedure;".

When you truncate, you need only enter enough characters of the command to distinguish the command from all other valid Debug Tool commands. You should *not* use truncations in a commands file or compile them into programs because they might become ambiguous in a subsequent release. The following shows examples of Debug Tool command truncations:

If you enter the following command...	It will be interpreted as...
A 3	AT 3
G	GO
Q B B	QUALIFY BLOCK B

If you enter the following command...	It will be interpreted as...
Q Q	QUERY QUALIFY
Q	QUIT

If you specify a truncation that is also a variable in your program, the keyword is chosen if this is the only ambiguity. For example, LIST A does not display the value of variable A, but executes the LIST AT command, listing your current AT breakpoints. To display the value of A, issue LIST (A).

In addition, ambiguous commands that cannot be resolved cause an error message and are not performed. That is, there are two commands that could be interpreted by the truncation specified. For example, D A A; is an ambiguous truncation since it could either be DESCRIBE ATTRIBUTES a; or DISABLE AT APPEARANCE;. Instead, you would have to enter DE A A; if you wanted DESCRIBE ATTRIBUTES a; or DI A A; if you wanted DISABLE AT APPEARANCE;. There are, of course, other variations that would work as well (for example, D ATT A;).

Entering multiline commands in full-screen and line mode

If you need to use more than one line when entering a command, you must use a continuation character.

When you are entering a command in interactive mode, the continuation character must be the last nonblank character in each line that is to be continued. In the following example:

```
LIST (" this is a very very very vvvvvvvvvvvvvvvvvvvvvvvvvvvvvvv -
very long string");
```

the continuation character is the single-byte character set (SBCS) hyphen (-).

If you want to end a line with a character that would be interpreted as a continuation character, follow that character with another valid nonblank character. For example, in C and C++, if you want to enter "i—", you could enter "(i—)" or "i—;". When the current programming language setting is C and C++, the back slash character (\) can also be used.

When Debug Tool is awaiting the continuation of a command in full-screen mode, you receive a continuation prompt of "MORE..." until the command is completely entered and processed. When continuation is indicated in line mode, you receive a continuation prompt of "PENDING..." until the command is completely entered and processed.

Entering multiline commands in a command file

The rules for line continuation when input comes from a commands file are language-specific:

- When the current programming language setting is C and C++, identifiers, keywords, and literals can be continued from one line to the next if the back slash continuation character is used. The following is an example of the continuation character for C:

```
LIST (" this is a very very very vvvvvvvvvvvvvvvvvvvvvvvvvvvvvv\
very long string");
```

- When the current programming language setting is COBOL, columns 1-6 are ignored by Debug Tool and input can be continued from one line to the next if

the SBCS hyphen (-) is used in column 7 of the next line. Command text must begin in column 8 or later and end in or before column 72.

In literal string continuation, an additional double (") or single (') quote is required in the continuation line, and the character following the quote is considered to follow immediately after the last character in the continued line. The following is an example of line continuation for COBOL:

```
123456 LIST (" this is a very very very vvvvvvvvvvvvvvvvvvvvvv"  
123456-"very long string");
```

Continuation is not allowed within a DBCS name or literal string when the current programming language setting is COBOL.

Entering multiline commands without continuation

You can enter the following command parts on separate lines without using the SBCS hyphen (-) continuation character:

- Subcommands and the END keyword in the PROCEDURE command
- When the current programming language setting is C, statements that are part of a compound or block statement
- When the current programming language setting is COBOL:
 - EVALUATE
 - Subcommands in WHEN and OTHER clauses
 - END-EVALUATE keyword
 - IF
 - Subcommands in THEN and ELSE clauses
 - END-IF keyword
 - PERFORM
 - Subcommands
 - Subcommands in UNTIL clause
 - END-PERFORM keyword

Using blanks in Debug Tool commands

Blanks cannot occur within keywords, identifiers, and numeric constants; however, they can occur within character strings. Blanks between keywords, identifiers, or constants are ignored except as delimiters. Blanks are required when no other delimiter exists and ambiguity is possible.

Entering comments in Debug Tool commands

Debug Tool lets you insert descriptive comments into the command stream (except within constants and other comments); however, the comment format depends on the current programming language. The entire line, including comments and delimiters, must not extend beyond column 72.

For C++ only: Comments in the form `"/"` are not processed by Debug Tool in C++.

- For all supported programming languages, comments can be entered by:
 - Enclosing the text in comment brackets `"/"` and `"/"`. Comments can occur anywhere a blank can occur between keywords, identifiers, and numeric constants. Comments entered in this manner do not appear in the session log.
 - Using the COMMENT command to insert commentary text in the session log. Comments entered in this manner cannot contain embedded semicolons.

- When the current programming language setting is COBOL, comments can also be entered by using an asterisk (*) in column 7. This is valid for file input only.
- For assembler and disassembly, comments can also be entered by using an asterisk (*) in column 1.

Comments are most helpful in file input. For example, you can insert comments in a USE file to explain and describe the actions of the commands.

Using constants in Debug Tool commands

Constants are entered as required by the current programming language setting. Most constants defined for each of the supported HLLs are also supported by Debug Tool.

Debug Tool allows the use of hexadecimal addresses in COBOL and PL/I.

The COBOL H constant is a fullword address value that can be specified in hex using numeric-hex-literal format (hexadecimal characters only, delimited by either double (") or single (') quotes and preceded by H). The value is right-justified and padded on the left with zeros.

Note: The H constant can only be used where an address or POINTER variable can be used. You can use this type of constant with the SET command. For example, to assign a hexadecimal value of 124BF to the variable *ptr*, specify:

```
SET ptr TO H"124BF";
```

The COBOL hexadecimal notation for alphanumeric literals, such as MOVE X'C1C2C3C4' TO NON-PTR-VAR, must be used for all other situations where a hexadecimal value is needed.

The PL/I PX constant is a hexadecimal value, delimited by single quotes (') and followed by PX. The value is right-justified and can be used in any context in which a pointer value is allowed. For example, to display the contents at a given address in hexadecimal format, specify:

```
LIST STORAGE ('20CD0'PX);
```

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using constants in COBOL expressions” on page 216

Related references

“C and C++ expressions” on page 241

Getting online help for Debug Tool command syntax

You can get help with Debug Tool command syntax by either pressing PF1 or entering a question mark (?) on the command line. This lists all Debug Tool commands in the Log window.

To get a list of options for a command, enter a partial command followed by a question mark.

For example, in full-screen mode, enter on the command line:

```
?  
WINDOW ?  
WINDOW CLOSE ?  
WINDOW CLOSE SOURCE
```

Now reopen the Source window with:

```
WINDOW OPEN SOURCE
```

to see the results.

The Debug Tool SYSTEM and TSO commands followed by ? do not invoke the syntax help; instead the ? is sent to the host as part of the system command. The COMMENT command followed by ? also does not invoke the syntax help.

Chapter 31. Debugging COBOL programs

Each version of the COBOL compiler provides enhancements that you can use to develop COBOL programs. These enhancements can create different levels of debugging capabilities. The topics below describe how to use these enhancements when you debug your COBOL programs.

“Format for a COBOL source listing and debug file”

“Qualifying variables and changing the point of view in COBOL” on page 217

“Debug Tool evaluation of COBOL expressions” on page 215

Chapter 23, “Debugging a COBOL program in full-screen mode,” on page 137

“Using COBOL variables with Debug Tool” on page 211

“Using DBCS characters in COBOL” on page 213

“Using Debug Tool functions with COBOL” on page 217

“Debug Tool commands that resemble COBOL statements”

“%PATHCODE values for COBOL” on page 214

“Debugging VS COBOL II programs” on page 220

Format for a COBOL source listing and debug file

Debug Tool can use COBOL source listings that are in a PDS, a sequential file, or an HFS file. The PDS or sequential file can be one of the following formats:

- Variable block.
- Fixed or fixed block with a record length of 133.

Debug Tool can use a separate debug file that is in a PDS, sequential file, or an HFS file. The format for a PDS file or a sequential file must be fixed or fixed block with a record length between 80 and 1024. You can create a separate debug file when you specify the SEPARATE suboption of the TEST compiler option. This suboption is available only on the following COBOL compilers:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298

Debug Tool commands that resemble COBOL statements

To test COBOL programs, you can write debugging commands that resemble COBOL statements. Debug Tool provides an interpretive subset of COBOL statements that closely resembles or duplicates the syntax and action of the appropriate COBOL statements. You can therefore work with familiar commands and insert into your source code program patches that you developed during your debug session.

The table below shows the interpretive subset of COBOL statements recognized by Debug Tool.

Command	Description
CALL	Subroutine call
COMPUTE	Computational assignment (including expressions)
Declarations	Declaration of session variables
EVALUATE	Multiway switch

Command	Description
IF	Conditional execution
MOVE	Noncomputational assignment
PERFORM	Iterative looping
SET	INDEX and POINTER assignment

This subset of commands is valid only when the current programming language is COBOL.

Related references

Debug Tool for z/OS Reference and Messages

COBOL command format

When you are entering commands directly at your terminal or workstation, the format is free-form, because you can begin your commands in column 1 and continue long commands using the appropriate method. You can continue on the next line during your Debug Tool session by using an SBCS hyphen (-) as a continuation character.

However, when you use a file as the source of command input, the format for your commands is similar to the source format for the COBOL compiler. The first six positions are ignored, and an SBCS hyphen in column 7 indicates continuation from the previous line. You must start the command text in column 8 or later, and end it in column 72.

The continuation line (with a hyphen in column 7) optionally has one or more blanks following the hyphen, followed by the continuing characters. In the case of the continuation of a literal string, an additional quote is required. When the token being continued is not a literal string, blanks following the last nonblank character on the previous line are ignored, as are blanks following the hyphen.

When Debug Tool copies commands to the log file, they are formatted according to the rules above so that you can use the log file during subsequent Debug Tool sessions.

Continuation is not allowed within a DBCS name or literal string. This restriction applies to both interactive and command file input.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“COBOL compiler options in effect for Debug Tool commands”

“COBOL reserved keywords” on page 211

Enterprise COBOL for z/OS and OS/390 Language Reference

COBOL compiler options in effect for Debug Tool commands

While Debug Tool allows you to use many commands that are either similar or equivalent to COBOL commands, Debug Tool does not necessarily interpret these commands according to the compiler options you chose when compiling your program. This is due to the fact that, in the Debug Tool environment, the following settings are in effect:

DYNAM
NOCMPR2
NODBCS

NOWORD
NUMPROC (NOPFD)
QUOTE
TRUNC (BIN)
ZWB

Related references

Enterprise COBOL for z/OS and OS/390 Language Reference

COBOL reserved keywords

In addition to the subset of COBOL commands you can use while in Debug Tool, there are reserved keywords used and recognized by COBOL that cannot be abbreviated, used as a variable name, or used as any other type of identifier.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Enterprise COBOL for z/OS and OS/390 Language Reference

Using COBOL variables with Debug Tool

Debug Tool can process all variable types valid in the COBOL language.

In addition to being allowed to assign values to variables and display the values of variables during your session, you can declare session variables to suit your testing needs.

“Example: assigning values to COBOL variables” on page 212

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Accessing COBOL variables”

“Assigning values to COBOL variables”

“Displaying values of COBOL variables” on page 213 “Declaring session variables in COBOL” on page 215

Accessing COBOL variables

Debug Tool obtains information about a program variable by name, using information that is contained in the symbol table built by the compiler. You make the symbol table available to Debug Tool by compiling with the TEST compiler option.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 5, “Preparing a COBOL program,” on page 25

Assigning values to COBOL variables

Debug Tool provides three COBOL-like commands to use when assigning values to variables: COMPUTE, MOVE, and SET. Debug Tool assigns values according to COBOL rules. See *Debug Tool for z/OS Reference and Messages* for tables that describe the allowable values for the source and receiver of the COMPUTE, MOVE, and SET commands.

Example: assigning values to COBOL variables

The examples for the COMPUTE, MOVE, and SET commands use the declarations defined in the following COBOL program segment.

```
01 GRP.
  02 ITM-1 OCCURS 3 TIMES INDEXED BY INX1.
    03 ITM-2 PIC 9(3) OCCURS 3 TIMES INDEXED BY INX2.
01 B.
  02 A      PIC 9(10).
01 D.
  02 C      PIC 9(10).
01 F.
  02 E      PIC 9(10) OCCURS 5 TIMES.
77 AA      PIC X(5)    VALUE 'ABCDE'.
77 BB      PIC X(5).
77 XX      PIC 9(9)    COMP.
77 ONE     PIC 99      VALUE 1.
77 TWO     PIC 99      VALUE 2.
77 PTR     POINTER.
```

Assign to variable xx the result of the expression $(a + e(1))/c * 2$.

```
COMPUTE xx =(a + e(1))/c * 2;
```

You can also use table elements in such assignments as shown in the following example:

```
COMPUTE itm-2(1,2)=(a + 1)/e(2);
```

The value assigned to a variable is always assigned to the storage for that variable. In an optimized program, a variable can be temporarily assigned to a register, and a new value assigned to that variable does not necessarily alter the value used by the program.

Assign to the program variable c , found in structure d , the value of the program variable a , found in structure b:

```
MOVE a OF b TO c OF d;
```

Note the qualification used in this example.

Assign the value of 123 to the first table element of itm-2:

```
MOVE 123 TO itm-2(1,1);
```

You can also use reference modification to assign values to variables as shown in the following two examples:

```
MOVE aa(2:3)TO bb;
MOVE aa TO bb(1:4);
```

Assign the value 3 to inx1, the index to itm-1:

```
SET inx1 TO 3;
```

Assign the value of inx1 to inx2:

```
SET inx2 TO inx1;
```

Assign the value of an invalid address (nonnumeric 0) to ptr:

```
SET ptr TO NULL;
```

Assign the address of XX to ptr:

```
SET ptr TO ADDRESS OF XX;
```

Assigns the hexadecimal value of X'20000' to the pointer ptr:
SET ptr TO H'20000';

Displaying values of COBOL variables

To display the values of variables, issue the LIST command. The LIST command causes Debug Tool to log and display the current values (and names, if requested) of variables. For example, if you want to display the variables aa, bb, one, and their respective values at statement 52 of your program, issue the following command:

```
AT 52 LIST TITLED (aa, bb, one); G0;
```

Debug Tool sets a breakpoint at statement 52 (AT), begins execution of the program (G0), stops at statement 52, and displays the variable names (TITLED) and their values.

Put commas between the variables when listing more than one. If you do not want to display the variable names when issuing the LIST command, issue LIST UNTITLED instead of LIST TITLED.

The value displayed for a variable is always the value that was saved in storage for that variable. In an optimized program, a variable can be temporarily assigned to a register, and the value shown for that variable might differ from the value being used by the program.

If you use the LIST command to display a National variable, Debug Tool converts the Unicode data to EBCDIC before displaying it. If the conversion results in characters that cannot be displayed, enter the LIST %HEX() command to display the unconverted Unicode data in hexadecimal format.

Using DBCS characters in COBOL

Programs you run with Debug Tool can contain variables and character strings written using the double-byte character set (DBCS). Debug Tool also allows you to issue commands containing DBCS variables and strings. For example, you can display the value of a DBCS variable (LIST), assign it a new value, monitor it in the monitor window (MONITOR), or search for it in a window (FIND).

To use DBCS with Debug Tool, enter:
SET DBCS ON;

If you are debugging in full-screen mode and your terminal is not DBCS capable, the SET DBCS ON is not available.

The DBCS default for COBOL is OFF.

The DBCS syntax and continuation rules you must follow to use DBCS variables in Debug Tool commands are the same as those for the COBOL language.

For COBOL you must type a DBCS literal, such as G, in front of a DBCS value in a Monitor or Data pop-up window if you want to update the value.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Enterprise COBOL for z/OS and OS/390 Language Reference

%PATHCODE values for COBOL

The table below shows the possible values for the Debug Tool variable %PATHCODE when the current programming language is COBOL.

-1	Debug Tool is not in control as the result of a path or attention situation.
0	Attention function (<i>not</i> ATTENTION condition).
1	A block has been entered.
2	A block is about to be exited.
3	Control has reached a label coded in the program (a paragraph name or section name).
4	Control is being transferred as a result of a CALL or INVOKE. The invoked routine's parameters, if any, have been prepared.
5	Control is returning from a CALL or INVOKE. If GPR 15 contains a return code, it has already been stored.
6	Some logic contained by an inline PERFORM is about to be executed. (Out-of-line PERFORM ranges must start with a paragraph or section name, and are identified by %PATHCODE = 3.)
7	The logic following an IF...THEN is about to be executed.
8	The logic following an ELSE is about to be executed.
9	The logic following a WHEN within an EVALUATE is about to be executed.
10	The logic following a WHEN OTHER within an EVALUATE is about to be executed.
11	The logic following a WHEN within a SEARCH is about to be executed.
12	The logic following an AT END within a SEARCH is about to be executed.
13	The logic following the end of one of the following structures is about to be executed: • An IF statement (with or without an ELSE clause) • An EVALUATE or SEARCH • A PERFORM
14	Control is about to return from a declarative procedure such as USE AFTER ERROR. (Declarative procedures must start with section names, and are identified by %PATHCODE = 3.)
15	The logic associated with one of the following phrases is about to be run: • [NOT] ON SIZE ERROR • [NOT] ON EXCEPTION • [NOT] ON OVERFLOW • [NOT] AT END (other than SEARCH AT END) • [NOT] AT END-OF-PAGE • [NOT] INVALID KEY
16	The logic following the end of a statement containing one of the following phrases is about to be run: • [NOT] ON SIZE ERROR • [NOT] ON EXCEPTION • [NOT] ON OVERFLOW • [NOT] AT END (other than SEARCH AT END) • [NOT] AT END-OF-PAGE • [NOT] INVALID KEY.

Note: Values in the range 3–16 can be assigned to %PATHCODE only if your program was compiled with an option supporting path hooks.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 5, “Preparing a COBOL program,” on page 25

Declaring session variables in COBOL

You might want to declare session variables during your Debug Tool session. The relevant variable assignment commands are similar to their counterparts in the COBOL language. The rules used for forming variable names in COBOL also apply to the declaration of session variables during a Debug Tool session.

The following declarations are for a string variable, a decimal variable, a pointer variable, and a floating-point variable. To declare a string named description, enter:

```
77 description      PIC X(25)
```

To declare a variable named numbers, enter:

```
77 numbers          PIC 9(4) COMP
```

To declare a pointer variable named pinkie, enter:

```
77 pinkie           POINTER
```

To declare a floating-point variable named shortfp, enter:

```
77 shortfp          COMP-1
```

Session variables remain in effect for the entire debug session.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using session variables across different languages” on page 306

Related references

Enterprise COBOL for z/OS and OS/390 Language Reference

Debug Tool evaluation of COBOL expressions

Debug Tool interprets COBOL expressions according to COBOL rules. Some restrictions do apply. For example, the following restrictions apply when arithmetic expressions are specified:

- Floating-point operands are not supported (COMP-1, COMP-2, external floating point, floating-point literals).
- Only integer exponents are supported.
- Intrinsic functions are not supported.
- Windowed date-field operands are not supported in arithmetic expressions in combination with any other operands.

When arithmetic expressions are used in relation conditions, both comparand attributes are considered. Relation conditions follow the IF rules rather than the EVALUATE rules.

Only simple relation conditions are supported. Sign conditions, class conditions, condition-name conditions, switch-status conditions, complex conditions, and abbreviated conditions are not supported. When either of the comparands in a

relation condition is stated in the form of an arithmetic expression (using operators such as plus and minus), the restriction concerning floating-point operands applies to both comparands. See *Debug Tool for z/OS Reference and Messages* for a table that describes the allowable comparisons for the IF command. See the *Enterprise COBOL for z/OS and OS/390 Programming Guide* for a description of the COBOL rules of comparison.

Windowed date fields are not supported in relation conditions.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Displaying the results of COBOL expression evaluation”

“Using constants in COBOL expressions”

Enterprise COBOL for z/OS and OS/390 Programming Guide

Related references

Debug Tool for z/OS Reference and Messages

Displaying the results of COBOL expression evaluation

Use the LIST command to display the results of your expressions. For example, to evaluate the expression and displays the result in the Log window, enter:

```
LIST a + (a - 10) + one;
```

You can also use structure elements in expressions. If e is an array, the following two examples are valid:

```
LIST a + e(1) / c * two;
```

```
LIST xx / e(two + 3);
```

Conditions for expression evaluation are the same ones that exist for program statements.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“COBOL compiler options in effect for Debug Tool commands” on page 210

Enterprise COBOL for z/OS and OS/390 Language Reference

Using constants in COBOL expressions

During your Debug Tool session you can use expressions that use string constants as one operand, as well as expressions that include variable names or number constants as single operands. All COBOL string constant types discussed in the *Enterprise COBOL for z/OS and OS/390 Language Reference* are valid in Debug Tool, with the following restrictions:

- The following COBOL figurative constants are supported:
 - ZERO, ZEROS, ZEROES
 - SPACE, SPACES
 - HIGH-VALUE, HIGH-VALUES
 - LOW-VALUE, LOW-VALUES
 - QUOTE, QUOTES
 - NULL, NULLS
 - Any of the above preceded by ALL
 - Symbolic-character (whether or not preceded by ALL).
- An N literal, which starts with N" or N', is always treated as a national literal.

Additionally, Debug Tool allows the use of a hexadecimal constant that represents an address. This *H-constant* is a fullword value that can be specified in hex using numeric-hex-literal format (hexadecimal characters only, delimited by either quotation marks (") or apostrophes (') and preceded by H). The value is right-justified and padded on the left with zeros. The following example:

```
LIST STORAGE (H'20cd0');
```

displays the contents at a given address in hexadecimal format. You can use this type of constant with the SET command. The following example:

```
SET ptr TO H'124bf';
```

assigns a hexadecimal value of 124bf to the variable ptr.

Using Debug Tool functions with COBOL

Debug Tool provides certain functions you can use to find out more information about program variables and storage.

Using %HEX with COBOL

You can use the %HEX function with the LIST command to display the hexadecimal value of an operand. For example, to display the external representation of the packed decimal pvar3, defined as PIC 9(9), from 1234 as its hexadecimal (or internal) equivalent, enter:

```
LIST %HEX (pvar3);
```

The Log window displays the hexadecimal string X'000001234'.

Using the %STORAGE function with COBOL

This Debug Tool function allows you to reference storage by address and length. By using the %STORAGE function as the reference when setting a CHANGE breakpoint, you can watch specific areas of storage for changes. For example, to monitor eight bytes of storage at the hex address 22222 for changes, enter:

```
AT CHANGE %STORAGE (H'00022222', 8)
  LIST 'Storage has changed at Hex address 22222'
```

Qualifying variables and changing the point of view in COBOL

Qualification is a method of specifying an object through the use of qualifiers, and changing the point of view from one block to another so you can manipulate data not known to the currently executing block. For example, the assignment MOVE 5 TO x; does not appear to be difficult for Debug Tool to process. However, you might have more than one variable named x. You must tell Debug Tool which variable x to assign the value of five.

You can use qualification to specify to what compile unit or block a particular variable belongs. When Debug Tool is invoked, there is a default qualification established for the currently executing block; it is *implicitly* qualified. Thus, you must explicitly qualify your references to all statement numbers and variable names in any other block. It is necessary to do this when you are testing a compile unit that calls one or more blocks or compile units. You might need to specify what block contains a particular statement number or variable name when issuing commands.

Qualifying variables in COBOL

Qualifiers are combinations of load modules, compile units, blocks, section names, or paragraph names punctuated by a combination of greater-than signs (>), colons, and the COBOL data qualification notation, OF or IN, that precede referenced statement numbers or variable names.

When qualifying objects on a block level, use only the COBOL form of data qualification. If data names are unique, or defined as GLOBAL, they do not need to be qualified to the block level.

The following is a fully qualified object:

```
load_name::>cu_name:>block_name:>object;
```

If required, *load_name* is the name of the load module. It is required only when the program consists of multiple load modules and you want to change the qualification to other than the current load module. *load_name* can also be the Debug Tool variable %LOAD.

If required, *cu_name* is the name of the compile unit. The *cu_name* must be the fully qualified compile unit name. It is required only when you want to change the qualification to other than the currently qualified compile unit. It can be the Debug Tool variable %CU.

If required, *block_name* is the name of the block. The *block_name* is required only when you want to change the qualification to other than the currently qualified block. It can be the Debug Tool variable %BLOCK. Remember to enclose the block name in double (") or single (') quotes if case sensitive. If the name is not inside quotes, Debug Tool converts the name to upper case.

Below are two similar COBOL programs (blocks).

```
MAIN
:
01  VAR1.
   02  VAR2.
       03  VAR3      PIC XX.
01  VAR4      PIC 99..

*****MOVE commands entered here*****

SUBPROG
:
01  VAR1.
   02  VAR2.
       03  VAR3      PIC XX.
01  VAR4      PIC 99.
01  VAR5      PIC 99.

*****LIST commands entered here*****
```

You can distinguish between the main and subprog blocks using qualification. If you enter the following MOVE commands when main is the currently executing block:

```
MOVE 8 TO var4;
MOVE 9 TO subprog:>var4;
MOVE 'A' TO var3 OF var2 OF var1;
MOVE 'B' TO subprog:>var3 OF var2 OF var1;
```

and the following LIST commands when subprog is the currently executing block:

```

LIST TITLED var4;
LIST TITLED main:>var4;
LIST TITLED var3 OF var2 OF var1;
LIST TITLED main:>var3 OF var2 OF var1;

```

each LIST command results in the following output (without the commentary) in your Log window:

```

VAR4 = 9;      /* var4 with no qualification refers to a variable      */
               /* in the currently executing block (subprog).                  */
               /* Therefore, the LIST command displays the value of 9.*/

MAIN:>VAR4 = 8  /* var4 is qualified to main.                                       */
               /* Therefore, the LIST command displays 8,                  */
               /* the value of the variable declared in main.      */

VAR3 OF VAR2 OF VAR1 = 'B';
               /* In this example, although the data qualification    */
               /* of var3 is OF var2 OF var1, the                      */
               /* program qualification defaults to the currently    */
               /* executing block and the LIST command displays      */
               /* 'B', the value declared in subprog.               */

VAR3 OF VAR2 OF VAR1 = 'A'
               /* var3 is again qualified to var2 OF var1          */
               /* but further qualified to main.                    */
               /* Therefore, the LIST command displays              */
               /* 'A', the value declared in main.                  */

```

The above method of qualifying variables is necessary for command files.

Changing the point of view in COBOL

The point of view is usually the currently executing block. You can also get to inaccessible data by changing the point of view using the SET QUALIFY command. The SET keyword is optional. For example, if the point of view (current execution) is in main and you want to issue several commands using variables declared in subprog, you can change the point of view by issuing the following:

```
QUALIFY BLOCK subprog;
```

You can then issue commands using the variables declared in subprog without using qualifiers. Debug Tool does not see the variables declared in procedure main. For example, the following assignment commands are valid with the subprog point of view:

```
MOVE 10 TO var5;
```

However, if you want to display the value of a variable in main while the point of view is still in subprog, you must use a qualifier, as shown in the following example:

```
LIST (main:>var-name);
```

The above method of changing the point of view is necessary for command files.

Considerations when debugging a COBOL class

The block structure of a COBOL class created with Enterprise COBOL for z/OS and OS/390, Version 3 Release 1 or later, is different from the block structure of a COBOL program. The block structure of a COBOL class has the following differences:

- The CLASS is a compile unit.
- The FACTORY paragraph is a block.

- The OBJECT paragraph is a block.
- Each method is a block.

A method belongs to either the FACTORY block or the OBJECT block. A fully qualified block name for a method in the FACTORY paragraph is:

```
class-name:>FACTORY:>method-name
```

A fully qualified block name for a method in the OBJECT paragraph is:

```
class-name:>OBJECT:>method-name
```

When you are at a breakpoint in a method, the currently qualified block is the method. If you enter the LIST TITLED command with no parameters, Debug Tool lists all of the data items associated with the method. To list all of the data items in a FACTORY or OBJECT, do the following steps:

1. Enter the QUALIFY command to set the point of view to the FACTORY or OBJECT.
2. Enter the LIST TITLED command.

For example, to list all of the object instance data items for a class called ACCOUNT, enter the following command:

```
QUALIFY BLOCK ACCOUNT:>OBJECT; LIST TITLED;
```

Debugging VS COBOL II programs

There are limitations to debugging VS COBOL II programs. Language Environment callable services, including CEETEST, are not available. However, you must use the Language Environment run time.

Debug Tool does not get control of the program at breakpoints that you set by the following commands:

- AT PATH
- AT CALL
- AT ENTRY
- AT EXIT

However, if you set the breakpoint with an AT CALL command that calls a non-VS COBOL II program, Debug Tool does get control of the program. Use the AT ENTRY *, AT EXIT *, AT GLOBAL ENTRY, and AT GLOBAL EXIT commands to set breakpoints that Debug Tool can use to get control of the program.

Breakpoints that you set at entry points and exit statements have no statement associated with them. Therefore, they are triggered only at the compile unit level. When they are triggered, the current view of the listing moves to the top and no statement is highlighted. Breakpoints that you set at entry points and exit statements are ignored by the STEP command.

If you are debugging your VS COBOL II program in remote debug mode, use the same TEST run-time options as for any COBOL program.

Finding the listing of a VS COBOL II program

The VS COBOL II compiler does not place the name of the listing data set in the object (load module). Debug Tool tries to find the listing data set in the following location: user.id.CUName.LIST. If the listing is in a PDS, direct Debug Tool to the location of the PDS in one of the following ways:

- In full-screen mode, enter the following command:
`SET DEFAULT LISTINGS my.listing.pds`
- In remote debug mode, add the `-qremote` option to the command that starts the daemon:
`idebug -qdaemon -quiport=8000 -qlang=cobol -qremotesource=my.listing.pds`
- Use the `EQADEBUG DD` statement to define the location of the data set.
- Code the `EQAUEDAT` user exit with the location of the data set.

For additional information on how you can debug VS COBOL II programs, see *Using CODE/370 with VS COBOL II and OS PL/I*, SC09-1862.

Chapter 32. Debugging an OS/VS COBOL program

You can use most of the Debug Tool commands to debug OS/VS COBOL programs that have debug information available. Any exceptions are noted in *Debug Tool for z/OS Reference and Messages*. Before debugging an OS/VS COBOL program, prepare your program as described in Chapter 6, “Preparing an OS/VS COBOL program,” on page 29.

As you read through the information in this document, remember that OS/VS COBOL programs are non-Language Environment programs, even though you might have used Language Environment libraries to link and run your program. Please read the information regarding non-Language Environment programs for instructions on how to start Debug Tool and debug OS/VS COBOL programs, unless OS/VS COBOL-specific information is provided.

Loading an OS/VS COBOL program's debug information

Use the LOADDEBUGDATA (LDD) command to indicate to Debug Tool that a compile unit is an OS/VS COBOL compile unit and to load the debug information associated with that compile unit. The LDD command can be used only for compile units that are considered disassembly compile units. In the following example, mypgm is the compile unit name of an OS/VS COBOL program: LDD mypgm

Debug Tool locates the debug information in a data set with the following name: yourid.EQALANGX(mypgm). If Debug Tool finds this data set, you can begin to debug your OS/VS COBOL program. If Debug Tool does not find the data set, enter the SET SOURCE or SET DEFAULT LISTINGS command to indicate to Debug Tool where to find the debug information. In remote debug mode, the remote debugger prompts you for the data set information when you step into the program.

Normally, compile units without debug information are not listed when you enter the DESCRIBE CUS or LIST NAMES CUS commands. To include these compile units, enter the SET ASSEMBLER ON command. The next time you enter the DESCRIBE CUS or LIST NAMES CUS command, these compile units are listed.

Debug Tool session panel while debugging an OS/VS COBOL program

The Debug Tool session panel below shows the information displayed in the Source window while you debug an OS/VS COBOL program.

```
1 OS COBOL LOCATION: COB030 initialization
Command ==>
MONITOR --+---1---+---2---+---3---+---4---+---5---+---6 LINE: 0 OF 0
***** TOP OF MONITOR *****
***** BOTTOM OF MONITOR *****
SOURCE: COB030 ---1---+---2---+---3---+---4---+---5---+ LINE: 1 OF 111
2 1 3 *****
2 * PROGRAM NAME: COB030 * .
3 * * * .
4 * COMPILED WITH IBM OS/VS COBOL COMPILER * .
5 ***** .
7 IDENTIFICATION DIVISION. .
8 PROGRAM-ID. COB030. .
9 ***** .
10 * .
11 * LICENSED MATERIALS - PROPERTY OF IBM .
12 * .
13 * 5655-M18: Debug Tool for z/OS .
14 * 5655-M19: Debug Tool Utilities and Advanced Functions for z/OS .
15 * (C) Copyright IBM Corp. 2004 All Rights Reserved .
16 * .
17 * US GOVERNMENT USERS RESTRICTED RIGHTS - USE, DUPLICATION OR .
18 * DISCLOSURE RESTRICTED BY GSA ADP SCHEDULE CONTRACT WITH IBM .
19 * CORP. .
20 * .
21 * .
22 ***** .
23 ENVIRONMENT DIVISION. .
24 DATA DIVISION. .
LOG 0---+---1---+---2---+---3---+---4---+---5---+---6- LINE: 1 OF 7
***** TOP OF LOG *****
0001 IBM Debug Tool Version 5 Release 1 Mod 0
0002 10/29/2004 09:52:48 AM
0003 5655-M18 and 5655-M19: (C) Copyright IBM Corp. 1992, 2004
0004 *** Commands file commands follow ***
0005 SET MSGID ON ;
0006 LDD ( COB030, COB03A0 ) ;
0007 EQA1891I *** Commands file commands end ***
***** BOTTOM OF LOG *****

PF 1:?      2:STEP      3:QUIT      4:LIST      5:FIND      6:AT/CLEAR
PF 7:UP      8:DOWN      9:GO       10:ZOOM     11:ZOOM LOG 12:RETRIEVE
```

The information displayed in the Source window is similar to the listing generated by the OS/VS COBOL compiler. The Source window displays the following information:

1 OS COBOL

This indicates that the current source program is OS/VS COBOL.

2 line number

The line number is a number assigned by the EQALANGX program by sequentially numbering the source lines. Use the numbers in this column to set breakpoints and identify statements.

3 source statement

The original source statement.

Restrictions for debugging an OS/VS COBOL program

When you debug OS/VS COBOL programs the following general restrictions apply:

- When you compose Debug Tool commands, all expressions must be enclosed in single-quotes
- The AT CALL command is not supported
- The AT EXIT command is not supported
- The STEP RETURN command is not supported
- If you enter a STEP command when stopped on a statement that returns control to a higher-level program, the STEP command acts like a G0 command.
- The only path-points for the AT PATH statement that are supported in an OS/VS COBOL program are Entry and Label.
- There are behavioral differences between OS/VS COBOL programs and other COBOL programs. OS/VS COBOL programs behaves more like assembler programs than COBOL programs in many situations. For example, in COBOL, a CU is not known to Debug Tool until it is called, even if it is statically link-edited into the same load module as the calling CU. However, OS/VS COBOL CU's are all known to Debug Tool when the module is loaded.
- The output of the DESCRIBE ATTRIBUTES command might not match the attributes originally coded in the following situations:
 - For packed decimal numbers (COMP-3) the PIC attribute always indicate an odd number of digits. This might be one more digit than was coded in the original PIC.
 - The only non-numeric PIC code that is displayed by Debug Tool is 'X'.

%PATHCODE values for OS/VS COBOL programs

This table shows the possible values for the Debug Tool variable %PATHCODE when the current programming language is OS/VS COBOL:

%PATHCODE	Entry Type
1	A block has been entered
3	Control has reached a label coded in the program.

Restrictions for debugging non-Language Environment programs

If you specify the TEST run-time option with the NOPROMPT suboption when you start your program, and Debug Tool is subsequently started by CALL CEETEST or the raising of an Language Environment condition, then you can debug both Language Environment and non-Language Environment programs and detect both Language Environment and non-Language Environment events in the enclave that started Debug Tool and in subsequent enclaves. You cannot debug non-Language Environment programs or detect non-Language Environment events in higher-level enclaves. After control has returned from the enclave in which Debug Tool was started, you can no longer debug non-Language Environment programs or detect non-Language Environment events.

Chapter 33. Debugging PL/I programs

The topics below describe how to use Debug Tool to debug your PL/I programs.

Refer to the following sections for more information related to the material discussed in this section.

Related concepts

“Debug Tool evaluation of PL/I expressions” on page 232

Related tasks

Chapter 25, “Debugging a PL/I program in full-screen mode,” on page 155

Chapter 33, “Debugging PL/I programs”

“Accessing PL/I program variables” on page 231

Related references

“Debug Tool subset of PL/I commands”

“Supported PL/I built-in functions” on page 232

Debug Tool subset of PL/I commands

The table below lists the Debug Tool *interpretive subset* of PL/I commands. This subset is a list of commands recognized by Debug Tool that either closely resemble or duplicate the syntax and action of the corresponding PL/I command. This subset of commands is valid only when the current programming language is PL/I.

Command	Description
Assignment	Scalar and vector assignment
BEGIN	Composite command grouping
CALL	Debug Tool procedure call
DECLARE or DCL	Declaration of session variables
DO	Iterative looping and composite command grouping
IF	Conditional execution
ON	Define an exception handler
SELECT	Conditional execution

PL/I language statements

PL/I statements are entered as Debug Tool *commands*. Debug Tool makes it possible to issue commands in a manner similar to each language.

The following types of Debug Tool commands will support the syntax of the PL/I statements:

Expression

This command evaluates an expression.

Block BEGIN/END, DO/END, PROCEDURE/END

These commands provide a means of grouping any number of Debug Tool commands into “one” command.

Conditional

IF/THEN, SELECT/WHEN/END

These commands evaluate an expression and control the flow of execution of Debug Tool commands according to the resulting value.

Declaration

DECLARE or DCL

These commands provide a means for declaring session variables.

Looping

DO/WHILE/UNTIL/END

These commands provide a means to program an iterative or conditional loop as a Debug Tool command.

Transfer of Control

GOTO, ON

These commands provide a means to unconditionally alter the flow of execution of a group of commands.

The table below shows the commands that are new or changed for this release of Debug Tool when the current programming language is PL/I.

Command	Description or changes
ANALYZE	Displays the PL/I style of evaluating an expression, and the precision and scale of the final and intermediate results. Debug Tool does not support this command for Enterprise PL/I programs.
ON	Performs as the AT OCCURRENCE command except it takes PL/I conditions as operands.
BEGIN	BEGIN/END blocks of logic.
DECLARE	Session variables can now include COMPLEX (CPLX), POINTER, BIT, BASED, ALIGNED, UNALIGNED, etc. Arrays can be declared to have upper and lower bounds. Variables can have precisions and scales. You cannot declare arrays and structures when you debug Enterprise PL/I programs.
DO	The three forms of DO are added; one is an extension of C's do. 1. DO; command(s); END; 2. DO WHILE UNTIL expression; command(s); END; 3. DO reference=specifications; command(s); END;
IF	The IF / ELSE does not require the ENDIF.
SELECT	The SELECT / WHEN / OTHERWISE / END programming structure is added.

%PATHCODE values for PL/I

The table below shows the possible values for the Debug Tool variable %PATHCODE when the current programming language is PL/I.

0	An attention interrupt occurred.
1	A block has been entered.
2	A block is about to be exited.
3	Control has reached a label constant.

4	Control is being sent somewhere else as the result of a CALL or a function reference.
5	Control is returning from a CALL invocation or a function reference. Register 15, if it contains a return code, has not yet been stored.
6	Some logic contained in a complex DO statement is about to be executed.
7	The logic following an IF..THEN is about to be executed.
8	The logic following an ELSE is about to be executed.
9	The logic following a WHEN within a <i>select-group</i> is about to be executed.
10	The logic following an OTHERWISE within a <i>select-group</i> is about to be executed.

PL/I conditions and condition handling

All PL/I conditions are recognized by Debug Tool. They are used with the AT OCCURRENCE and ON commands.

When an OCCURRENCE breakpoint is triggered, the Debug Tool %CONDITION variable holds the following values:

Triggered condition	%CONDITION value
AREA	AREA
ATTENTION	CEE35J
COND (CC#1)	CONDITION
CONVERSION	CONVERSION
ENDFILE (MF)	ENDFILE
ENDPAGE (MF)	ENDPAGE
ERROR	ERROR
FINISH	CEE066
FOFL	CEE348
KEY (MF)	KEY
NAME (MF)	NAME
OVERFLOW	CEE34C
PENDING (MF)	PENDING
RECORD (MF)	RECORD
SIZE	SIZE
STRG	STRINGRANGE
STRINGSIZE	STRINGSIZE
SUBRG	SUBSCRIPTRANGE
TRANSMIT (MF)	TRANSMIT
UNDEFINEDFILE (MF)	UNDEFINEDFILE
UNDERFLOW	CEE34D
ZERODIVIDE	CEE349

Note: For Enterprise PL/I programs, the following conditions are not supported:

- AT OCCURRENCE file conditions (ENDFILE, ENDPAGE, KEY, NAME, RECORD, TRANSMIT, UNDEFINEDFILE)

- AT OCCURRENCE CONDITION conditions (name)

Note: The Debug Tool condition ALLOCATE raises the ON ALLOCATE condition when a PL/I program encounters an ALLOCATE statement for a controlled variable.

These PL/I language-oriented commands are only a subset of all the commands that are supported by Debug Tool.

Entering commands in PL/I DBCS freeform format

Statements can be entered in PL/I's DBCS freeform. This means that statements can freely use shift codes as long as the statement is not ambiguous.

This will change the description or characteristics of LIST NAMES in that:

```
LIST NAMES db<.c.skk.w>ord
```

will search for

```
<.D.B.C.Skk.W.O.R.D>
```

This will result in different behavior depending upon the language. For example, the following will find a<kk>b in C and <.Akk.b> in PL/I.

```
LIST NAMES a<kk>*
```

where <kk> is shiftout-kanji-shiftin.

Freeform will be added to the parser and will be in effect while the current programming language is PL/I.

Initializing Debug Tool when TEST(ERROR, ...) run-time option is in effect

With the run-time option, TEST(ERROR, ...) only the following can initialize Debug Tool:

- The ERROR condition
- Attention recognition
- CALL PLITEST
- CALL CEETEST

Debug Tool enhancements to LIST STORAGE PL/I command

LIST STORAGE address has been enhanced so that the address can be a POINTER, a Px constant, or the ADDR built-in function.

PL/I support for Debug Tool session variables

PL/I will support all Debug Tool scalar session variables. In addition, arrays and structures can be declared.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using session variables across different languages” on page 306

Accessing PL/I program variables

Debug Tool obtains information about a program variable by name using information that is contained in the symbol table built by the compiler. The symbol table is made available to the compiler by compiling with TEST(SYM).

Debug Tool uses the symbol table to obtain information about program variables, controlled variables, automatic variables, and program control constants such as file and entry constants and also CONDITION condition names. Based variables, controlled variables, automatic variables and parameters can be used with Debug Tool only after storage has been allocated for them in the program. An exception to this is DESCRIBE ATTRIBUTES, which can be used to display attributes of a variable.

Variables that are based on:

- An OFFSET variable,
- An expression, or
- A pointer that either is based or defined, a parameter, or member of either an array or a structure

must be explicitly qualified when used in expressions. For example, assume you made the following declaration:

```
DECLARE P1 POINTER;  
DECLARE P2 POINTER BASED(P1);  
DECLARE DX FIXED BIN(31) BASED(P2);
```

You would not be able to reference the variable directly by name. You can only reference it by specifying either:

```
P2->DX  
or  
P1->P2->DX
```

The following types of program variables cannot be used with Debug Tool:

- iSUB defined variables
- Variables defined:
 - On a controlled variable
 - On an array with one or more adjustable bounds
 - With a POSITION attributed that specifies something other than a constant
- Variables that are members of a based structure declared with the REFER options.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 7, “Preparing a PL/I program,” on page 33

Accessing PL/I structures

You cannot reference elements of arrays of structures. For example, suppose a structure called PAYROLL is declared as follows:

```
Declare 1 Payroll(100),  
       2 Name,  
         4 Last      char(20),  
         4 First     char(15),  
       2 Hours,  
         4 Regular   Fixed Decimal(5,2),  
         4 Overtime  Fixed Decimal(5,2);
```

Given the way PAYROLL is declared, the following examples of commands are **valid** in Debug Tool:

```
LIST ( PAYROLL(1).NAME.LAST, PAYROLL(1).HOURS.REGULAR );
```

```
LIST ( ADDR ( PAYROLL ) );
```

```
LIST STORAGE ( PAYROLL.HOURS, 128 );
```

Given the way PAYROLL is declared, the following examples of commands are **invalid** in Debug Tool:

```
LIST ( PAYROLL(1) );
```

```
LIST (ADDR ( PAYROLL(5) ) );
```

```
LIST STORAGE ( PAYROLL(15).HOURS, 128 ) );
```

Debug Tool evaluation of PL/I expressions

When the current programming language is PL/I, expression interpretation is similar to that defined in the PL/I language, except for the PL/I language elements not supported in Debug Tool.

The Debug Tool expression is similar to the PL/I expression. If the source of the command is a variable-length record source (such as your terminal) and if the expression extends across more than one line, a continuation character (an SBCS hyphen) must be specified at the end of all but the last line.

All PL/I constant types are supported, plus the Debug Tool PX constant.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Unsupported PL/I language elements” on page 234

Supported PL/I built-in functions

Debug Tool supports the following built-in functions for PL/I for MVS & VM:

ABS	CSTG ²	LOG1	REAL
ACOS	CURRENTSTORAGE	LOG2	REPEAT
ADDR	DATAFIELD	LOW	SAMEKEY
ALL	DATE	MPSTR	SIN
ALLOCATION	DATETIME	NULL	SIND
ANY	DIM	OFFSET	SINH
ASIN	EMPTY	ONCHAR	SQRT
ATAN	ENTRYADDR	ONCODE	STATUS
ATAND	ERF	ONCOUNT	STORAGE
ATANH	ERFC	ONFILE	STRING
BINARYVALUE	EXP	ONKEY	SUBSTR
BINVALUE ¹	GRAPHIC	ONLOC	SYSNULL
BIT	HBOUND	ONSOURCE	TAN
BOOL	HEX	PLIRETV	TAND
CHAR	HIGH	POINTER	TANH
COMPLETION	IMAG	POINTERADD	TIME
COS	LBOUND	POINTERVALUE	TRANSLATE
COSD	LENGTH	PTRADD ³	UNSPEC
COSH	LINENO	PTRVALUE ⁴	VERIFY
COUNT	LOG		

Notes:

1. Abbreviation for BINARYVALUE
2. Abbreviation for CURRENTSTORAGE
3. Abbreviation for POINTERADD
4. Abbreviation for POINTERVALUE

Debug Tool supports the following built-in functions for Enterprise PL/I:

ACOS	HEXIMAGE	OFFSETVALUE	POINTERDIFF
ADDR	HIGH ¹	ORDINALNAME	PTRDIFF
ASIN	IAND	ORDINALPRED	POINTERVALUE
ATAN	IEOR	ORDINALSUCC	PTRVALUE
ATAND	IOR	ONCODE	PLIRETV
ATANH	INDEX	ONCONDCOND	RAISE2
BIF_DIM	INOT	ONCHAR	REPEAT ¹
BINARYVALUE	ISRL	ONGSOURCE	SAMEKEY
BINVALUE	ISLL	ONSOURCE	SEARCH
COPY ¹	LBOUND	ONCONDID	SEARCHR
COS	LENGTH	ONCOUNT	SIN
COSD	LINENO	ONFILE	SIND
COSH	LOG	ONKEY	SINH
COUNT	LOG10	ONLOC	SQRT
DATAFIELD	LOG2	PAGENO	SUBSTR ¹
DATE ¹	LOGGAMMA	POINTER	SYSNULL
DATETIME ¹	LOW ¹	PTR	TAN
DIMENSION	LOWER2	POINTERADD	TAND
ENDFILE	LOWERCASE ¹	PTRADD	TANH
ENTRYADDR ^{1,2}	MAXLENGTH	POINTERSUBTRACT	TALLY
ERF	NULL	PTRSUBTRACT	TIME ¹
ERFC	OFFSET		TRANSLATE ¹
EXP	OFFSETADD		UNSPEC ¹
FILEOPEN	OFFSETSUBTRACT		UPPERCASE ¹
GAMMA	OFFSETDIFF		VERIFY
HBOUND			VERIFYR
HEX			

Notes:

1. You must apply the Language Environment run-time PTF for APAR PQ94347 (available for z/OS Version 1 Release 4, Version 1 Release 5, and Version 1 Release 6) to use the built-in functions COPY, DATE, DATETIME, ENTRYADDR, HIGH, LOW, LOWERCASE, REPEAT, SUBSTR, TIME, TRANSLATE, UNSPEC, and UPPERCASE.
2. Pseudovariables are not supported for the ENTRYADDR built-in function under Debug Tool.

Debug Tool does not support the following built-in functions for Enterprise PL/I:

ABS	CURRENTSTORAGE
ALL	EMPTY
ALLOCATION	GRAPHIC
ANY	IMAG
BIT	MPSTR
BOOL	REAL
CHAR	STATUS
COMPLETION	STORAGE
CSTG(2)	STRING

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using SET WARNING PL/I command with built-in functions”

Using SET WARNING PL/I command with built-in functions

Certain checks are performed when the Debug Tool SET WARNING command setting is ON and a built-in function (BIF) is evaluated:

- Division by zero
- The remainder (%) operator for a zero value in the second operand
- Array subscript out of bounds for defined arrays
- Bit shifting by a number that is negative or greater than 32
- On a built-in function call for an incorrect number of parameters or for parameter type mismatches
- On a built-in function call for differing linkage calling conventions

These checks are restrictions that can be removed by issuing SET WARNING OFF.

Unsupported PL/I language elements

The following list summarizes PL/I functions not available:

- Use of iSUB
- Interactive declaration or use of user-defined functions
- All preprocessor directives
- Multiple assignments
- BY NAME assignments
- LIKE attribute
- FILE, PICTURE, and ENTRY data attributes
- All I/O statements, including DISPLAY
- INIT attribute
- Structures with the built-in functions CSTG, CURRENTSTORAGE, and STORAGE
- The repetition factor is not supported for string constants
- GRAPHIC string constants are not supported for expressions involving other data types
- Declarations cannot be made as sub-commands (for example in a BEGIN, DO, or SELECT command group)

Debugging OS PL/I programs

There are restrictions on how you can debug OS PL/I programs, which are described in *Using CODE/370 with VS COBOL II and OS PL/I*, SC09-1862-01.

The OS PL/I compiler does not place the name of the listing data set in the object (load module). Debug Tool tries to find the listing data set in the following location: `userid.CUName.LIST`. If the listing is in a PDS, direct Debug Tool to the location of the PDS in one of the following ways:

- In full-screen mode, enter the following command:
`SET DEFAULT LISTINGS my.listing.pds`
- Use the EQADEBUG DD statement to define the location of the data set.
- Code the EQAUEDAT user exit with the location of the data set.

Restrictions while debugging Enterprise PL/I programs

While debugging Enterprise PL/I programs, you cannot use the following commands:

- ANALYZE
- AT ALLOCATE (of a controlled variable)
- AT OCCURRENCE (for file conditions: ENDFILE, ENDPAGE, KEY, NAME, RECORD, TRANSMIT, UNDEFINEDFILE)
- AT OCCURRENCE CONDITION conditions (name)
- DESCRIBE ATTRIBUTES
- GOTO LABEL

While debugging Enterprise PL/I programs, the following restrictions apply:

- If you want to use the AT LABEL command, be aware of the following restrictions:
 - If you are running any version of VisualAge PL/I or Enterprise PL/I Version 3 Release 1 through Version 3 Release 3 programs, you cannot use the AT LABEL command.
 - If you are running Enterprise PL/I Version 3 Release 4 programs and you comply with the following requirements, you can use the AT LABEL command to set breakpoints (except at a label variable):
 - You are running on z/OS Version 1 Release 4 or later.
 - You apply PTF for APAR PQ99039 to the z/OS Language Environment run-time.
 - You apply PTFs for APARs PK00118 and PK00339 to the Enterprise PL/I Version 3 Release 4 compiler.
- For expressions, you cannot do either of the following:
 - preface variables with the block, CU, and load module qualification
 - Reference or list at the block entry
- You cannot use some of built-in functions. See “Supported PL/I built-in functions” on page 232 for more information.
- You cannot use the DECLARE command to declare arrays, structures, or multiple variables in one line
- The SET WARNING ON command has no effect.
- If you apply the Language Environment run-time PTF for APAR PQ95664 (available for z/OS Version 1 Release 3 through Version 1 Release 6), you can use the DESCRIBE ENVIRONMENT command.

Chapter 34. Debugging C and C++ programs

The topics below describe how to use Debug Tool to debug your C and C++ programs.

"Example: referencing variables and setting breakpoints in C and C++ blocks" on page 251

Refer to the following sections for more information related to the material discussed in this section.

Related concepts

"C and C++ expressions" on page 241

"Debug Tool evaluation of C and C++ expressions" on page 245

"Scope of objects in C and C++" on page 248

"Blocks and block identifiers for C" on page 250

"Blocks and block identifiers for C++" on page 250

"Monitoring storage in C++" on page 258

Related tasks

Chapter 26, "Debugging a C program in full-screen mode," on page 163

Chapter 27, "Debugging a C++ program in full-screen mode," on page 173

"Using C and C++ variables with Debug Tool" on page 238

"Declaring session variables with C and C++" on page 240

"Calling C and C++ functions from Debug Tool" on page 242

"Intercepting files when debugging C and C++ programs" on page 246

"Displaying environmental information" on page 252

"Stepping through C++ programs" on page 255

"Setting breakpoints in C++" on page 255

"Examining C++ objects" on page 257

"Qualifying variables in C and C++" on page 253

Related references

"Debug Tool commands that resemble C and C++ commands"

"%PATHCODE values for C and C++" on page 240

"C reserved keywords" on page 243

"C operators and operands" on page 243

"Language Environment conditions and their C and C++ equivalents" on page 244

Debug Tool commands that resemble C and C++ commands

Debug Tool's command language is a subset of C and C++ commands and has the same syntactical requirements. Debug Tool allows you to work in a language you are familiar with so learning a new set of commands is not necessary.

The table below shows the interpretive subset of C and C++ commands recognized by Debug Tool.

Command	Description
block ({})	Composite command grouping
break	Termination of loops or switch commands
declarations	Declaration of session variables
do/while	Iterative looping

Command	Description
expression	Any C expression except the conditional (?) operator
for	Iterative looping
if	Conditional execution
switch	Conditional execution

This subset of commands is valid only when the current programming language is C or C++.

In addition to the subset of C and C++ commands that you can use is a list of reserved keywords used and recognized by C and C++ that you cannot abbreviate, use as variable names, or use as any other type of identifier.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“C reserved keywords” on page 243

C/C++ Language Reference

Using C and C++ variables with Debug Tool

Debug Tool can process all program variables that are valid in C or C++. You can assign and display the values of variables during your session. You can also declare session variables with the recognized C declarations to suit your testing needs.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Accessing C and C++ program variables”

“Displaying values of C and C++ variables or expressions”

“Assigning values to C and C++ variables” on page 239

Accessing C and C++ program variables

Debug Tool obtains information about a program variable by name using the symbol table built by the compiler. If you specify TEST(SYM) at compile time, the compiler builds a symbol table that allows you to reference any variable in the program.

Note: There are no suboptions for C++. Symbol information is generated by default when the TEST compiler option is specified.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 8, “Preparing a C program,” on page 37

Chapter 9, “Preparing a C++ program,” on page 41

Displaying values of C and C++ variables or expressions

To display the values of variables or expressions, use the LIST command. The LIST command causes Debug Tool to log and display the current values (and names, if requested) of variables, including the evaluated results of expressions.

Suppose you want to display the program variables `X`, `row[X]`, and `col[X]`, and their values at line 25. If you issue the following command:

```
AT 25 LIST ( X, row[X], col[X] ); G0;
```

Debug Tool sets a breakpoint at line 25 (AT), begins execution of the program (G0), stops at line 25, and displays the variable names and their values.

If you want to see the result of their addition, enter:

```
AT 25 LIST ( X + row[X] + col[X] ); G0;
```

Debug Tool sets a breakpoint at line 25 (AT), begins execution of the program (G0), stops at line 25, and displays the result of the expression.

Put commas between the variables when listing more than one. If you do not want to display the variable names when issuing the LIST command, enter LIST UNTITLED.

You can also list variables with the `printf` function call as follows:

```
printf ("X=%d, row=%d, col=%d\n", X, row[X], col[X]);
```

The output from `printf`, however, does not appear in the Log window and is not recorded in the log file unless you SET INTERCEPT ON FILE stdout.

Assigning values to C and C++ variables

To assign a value to a C and C++ variable, you use an assignment expression. Assignment expressions assign a value to the left operand. The left operand must be a modifiable lvalue. An lvalue is an expression representing a data object that can be examined and altered.

C contains two types of assignment operators: simple and compound. A simple assignment operator gives the value of the right operand to the left operand.

Note: Only the assignment operators that work for C will work for C++, that is, there is no support for overloaded operators.

The following example demonstrates how to assign the value of `number` to the member `employee` of the structure `payroll`:

```
payroll.employee = number;
```

Compound assignment operators perform an operation on both operands and give the result of that operation to the left operand. For example, this expression gives the value of `index` plus 2 to the variable `index`:

```
index += 2
```

Debug Tool supports all C operators except the ternary operator, as well as any other full C language assignments and function calls to user or C library functions.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Calling C and C++ functions from Debug Tool” on page 242

%PATHCODE values for C and C++

The table below shows the possible values for the Debug Tool variable %PATHCODE when the current programming language is C and C++.

-1	Debug Tool is not in control as the result of a path or attention situation.
0	Attention function (<i>not</i> ATTENTION condition).
1	A block has been entered.
2	A block is about to be exited.
3	Control has reached a user label.
4	Control is being transferred as a result of a function reference. The invoked routine's parameters, if any, have been prepared.
5	Control is returning from a function reference. Any return code contained in register 15 has not yet been stored.
6	Some logic contained by a conditional do/while, for, or while statement is about to be executed. This can be a single or Null statement and not a block statement.
7	The logic following an if(...) is about to be executed.
8	The logic following an else is about to be executed.
9	The logic following a case within an switch is about to be executed.
10	The logic following a default within a switch is about to be executed.
13	The logic following the end of a switch, do, while, if(...), or for is about to be executed.
17	A goto, break, continue, or return is about to be executed.

Values in the range 3–17 can only be assigned to %PATHCODE if your program was compiled with an option supporting path hooks.

Declaring session variables with C and C++

You might want to declare session variables for use during the course of your session. You cannot initialize session variables in declarations. However, you can use an assignment statement or function call to initialize a session variable.

As in C, keywords can be specified in any order. Variable names up to 255 characters in length can be used. Identifiers are case-sensitive, but if you want to use the session variable when the current programming language changes from C to another HLL, the variable must have an uppercase name and compatible attributes.

To declare a hexadecimal floating-point variable called maximum, enter the following C declaration:

```
double maximum;
```

You can only declare scalars, arrays of scalars, structures, and unions in Debug Tool (pointers for the above are allowed as well).

If you declare a session variable with the same name as a programming variable, the session variable hides the programming variable. To reference the programming variable, you must qualify it. For example:

```
main:>x for the program variable x
x for the session variable x
```

Session variables remain in effect for the entire debug session, unless they are cleared using the CLEAR command.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using session variables across different languages” on page 306

“Qualifying variables and changing the point of view in C and C++” on page 252

C and C++ expressions

Debug Tool allows evaluation of expressions in your test program. All expressions available in C and C++ are also available within Debug Tool except for the conditional expression (? :). That is, all operators such as +, -, %:, and += are fully supported with the exception of the conditional operator.

C and C++ language expressions are arranged in the following groups based on the operators they contain and how you use them:

- Primary expression
- Unary expression
- Binary expression
- Conditional expression
- Assignment expression
- Comma expression
- lvalue
- Constant

An lvalue is an expression representing a data object that can be examined and altered. For a more detailed description of expressions and operators, see the C and C++ Program Guides.

The semantics for C and C++ operators are the same as in a compiled C or C++ program. Operands can be a mixture of constants (integer, floating-point, character, string, and enumeration), C and C++ variables, Debug Tool variables, or session variables declared during a Debug Tool session. Language constants are specified as described in the C and C++ Language Reference publications.

The Debug Tool command DESCRIBE ATTRIBUTES can be used to display the resultant type of an expression, without actually evaluating the expression.

The C and C++ language does not specify the order of evaluation for function call arguments. Consequently, it is possible for an expression to have a different execution sequence in compiled code than within Debug Tool. For example, if you enter the following in an interactive session:

```
int x;
int y;

x = y = 1;

printf ("%d %d %d%" x, y, x=y=0);
```

the results can differ from results produced by the same statements located in a C or C++ program segment. Any expression containing behavior undefined by ANSI standards can produce different results when evaluated by Debug Tool than when evaluated by the compiler.

The following examples show you various ways Debug Tool supports the use of expressions in your programs:

- Debug Tool assigns 12 to a (the result of the `printf()` function call, as in:

```
a = (1,2/3,a++,b++,printf("hello world\n"));
```
- Debug Tool supports structure and array referencing and pointer dereferencing, as in:

```
league[num].team[1].player[1]++;  
league[num].team[1].total += 1;  
++(*pleague);
```
- Simple and compound assignment is supported, as in:

```
v.x = 3;  
a = b = c = d = 0;  
*(pointer++) -= 1;
```
- C and C++ language constants in expressions can be used, as in:

```
pointer_to_c = "abcdef" + 0x2;  
*pointer_to_long = 3521L = 0x69a1;  
float_val = 3e-11 + 6.6E-10;  
char_val = '7';
```
- The comma expression can be used, as in:

```
intensity <= 1, shade * increment, rotate(direction);  
alpha = (y>>3, omega % 4);
```
- Debug Tool performs all implicit and explicit C conversions when necessary. Conversion to long double is performed in:

```
long_double_val = unsigned_short_val;  
long_double_val = (long double) 3;
```

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Debug Tool evaluation of C and C++ expressions” on page 245
C/C++ Language Reference

Calling C and C++ functions from Debug Tool

You can perform calls to user and C library functions within Debug Tool.

You can make calls to C library functions at any time. In addition, you can use the C library variables `stdin`, `stdout`, `stderr`, `__amrc`, and `errno` in expressions including function calls.

The library function `ctdl_i` cannot be called unless it is referenced in a compile unit in the program, either `main` or a function linked to `main`.

Calls to user functions can be made, provided Debug Tool is able to locate an appropriate definition for the function within the symbol information in the user program. These definitions are created when the program is compiled with `TEST(SYM)` for C or `TEST` for C++.

Debug Tool performs parameter conversions and parameter-mismatch checking where possible. Parameter checking is performed if:

- The function is a library function
- A prototype for the function exists in the current compile unit
- Debug Tool is able to locate a prototype for the function in another compile unit, or the function itself was compiled with `TEST(SYM)` for C or with `TEST` for C++.

You can turn off this checking by specifying SET WARNING OFF.

Calls can be made to any user functions that have linkage supported by the C or C++ compiler. However, for C++ calls made to any user function, the function must be declared as:

```
extern "C"
```

For example, use this declaration if you want to debug an application signal handler. When a condition occurs, control passes to Debug Tool which then passes control to the signal handler.

Debug Tool attempts linkage checking, and does not perform the function call if it determines there is a linkage mismatch. A linkage mismatch occurs when the target program has one linkage but the source program believes it has a different linkage.

It is important to note the following regarding function calls:

- The evaluation order of function arguments can vary between the C and C++ program and Debug Tool. No discernible difference exists if the evaluation of arguments does not have side effects.
- Debug Tool knows about the function return value, and all the necessary conversions are performed when the return value is used in an expression.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 8, "Preparing a C program," on page 37

Chapter 9, "Preparing a C++ program," on page 41

Related references

C/C++ Language Reference

C reserved keywords

The table below lists all keywords reserved by the C language. When the current programming language is C or C++, these keywords cannot be abbreviated, used as variable names, or used as any other type of identifiers.

auto	else	long	switch
break	enum	register	typedef
case	extern	return	union
char	float	short	unsigned
const	for	signed	void
continue	goto	sizeof	volatile
default	if	static	while
do	int	struct	_Packed
double			

C operators and operands

The table below lists the C language operators in order of precedence and shows the direction of associativity for each operator. The primary operators have the highest precedence. The comma operator has the lowest precedence. Operators in the same group have the same precedence.

Precedence level	Associativity	Operators
Primary	left to right	() [] . ->
Unary	right to left	++ -- - + ! ~ & * (typename) sizeof
Multiplicative	left to right	* / %
Additive	left to right	+ -
Bitwise shift	left to right	<< >>
Relational	left to right	< > <= >=
Equality	left to right	== !=
Bitwise logical AND	left to right	&
Bitwise exclusive OR	left to right	^ or ~
Bitwise inclusive OR	left to right	
Logical AND	left to right	&&
Logical OR	left to right	
Assignment	right to left	= += -= *= /= <<= >>= %= &= ^= =
Comma	left to right	,

Language Environment conditions and their C and C++ equivalents

Language Environment condition names (the symbolic feedback codes CEExxx) can be used interchangeably with the equivalent C and C++ conditions listed in the following table. For example, AT OCCURRENCE CEE341 is equivalent to AT OCCURRENCE SIGILL. Raising a CEE341 condition triggers an AT OCCURRENCE SIGILL breakpoint and vice versa.

Language Environment condition	Description	Equivalent C/C++ condition
CEE341	Operation exception	SIGILL
CEE342	Privileged operation exception	SIGILL
CEE343	Execute exception	SIGILL
CEE344	Protection exception	SIGSEGV
CEE345	Addressing exception	SIGSEGV
CEE346	Specification exception	SIGILL
CEE347	Data exception	SIGFPE
CEE348	Fixed point overflow exception	SIGFPE
CEE349	Fixed point divide exception	SIGFPE
CEE34A	Decimal overflow exception	SIGFPE
CEE34B	Decimal divide exception	SIGFPE
CEE34C	Exponent overflow exception	SIGFPE
CEE34D	Exponent underflow exception	SIGFPE
CEE34E	Significance exception	SIGFPE
CEE34F	Floating-point divide exception	SIGFPE

Debug Tool evaluation of C and C++ expressions

Debug Tool interprets most input as a collection of one or more expressions. You can use expressions to alter a program variable or to extend the program by adding expressions at points that are governed by AT breakpoints.

Debug Tool evaluates C and C++ expressions following the rules presented in *C/C++ Language Reference*. The result of an expression is equal to the result that would have been produced if the same expression had been part of your compiled program.

Implicit string concatenation is supported. For example, "abc" "def" is accepted for "abcdef" and treated identically. Concatenation of wide string literals to string literals is not accepted. For example, L"abc"L"def" is valid and equivalent to L"abcdef", but "abc" L"def" is not valid.

Expressions you use during your session are evaluated with the same sensitivity to enablement as are compiled expressions. Conditions that are enabled are the same ones that exist for program statements.

During a Debug Tool session, if the current setting for WARNING is ON, the occurrence in your C or C++ program of any one of the conditions listed below causes the display of a diagnostic message.

- Division by zero
- Remainder (%) operator for a zero value in the second operand
- Array subscript out of bounds for a defined array
- Bit shifting by a number that is either negative or greater than 32
- Incorrect number of parameters, or parameter type mismatches for a function call
- Differing linkage calling conventions for a function call
- Assignment of an integer value to a variable of enumeration data type where the integer value does not correspond to an integer value of one of the enumeration constants of the enumeration data type
- Assignment to an lvalue that has the const attribute
- Attempt to take the address of an object with register storage class
- A signed integer constant not in the range -2^{31} to 2^{31}
- A real constant not having an exponent of 3 or fewer digits
- A float constant not larger than 5.39796053469340278908664699142502496E-79 or smaller than 7.2370055773322622139731865630429929E+75
- A hex escape sequence that does not contain at least one hexadecimal digit
- An octal escape sequence with an integer value of 256 or greater
- An unsigned integer constant greater than the maximum value of 4294967295.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“C and C++ expressions” on page 241

C/C++ Language Reference

Intercepting files when debugging C and C++ programs

Several considerations must be kept in mind when using the SET INTERCEPT command to intercept files while you are debugging a C application.

For CICS only: SET INTERCEPT is not supported for CICS.

For C++, there is no specific support for intercepting IOStreams. IOStreams is implemented using C I/O which implies that:

- If you intercept I/O for a C standard stream, this implicitly intercepts I/O for the corresponding IOStreams' standard stream.
- If you intercept I/O for a file, by name, and define an IOStream object associated with the same file, IOStream I/O to that file will be intercepted.

Note: Although you can intercept IOStreams indirectly via C/370 I/O, the behaviors might be different or undefined in C++.

You can use the following names with the SET INTERCEPT command during a debug session:

- stdout, stderr, and stdin (lowercase only)
- any valid fopen() file specifier.

The behavior of I/O interception across system() call boundaries is global. This implies that the setting of INTERCEPT ON for xx in Program A is also in effect for Program B (when Program A system() calls to Program B). Correspondingly, setting INTERCEPT OFF for xx in Program B turns off interception in Program A when Program B returns to A. This is also true if a file is intercepted in Program B and returns to Program A. This model applies to disk files, memory files, and standard streams.

When a stream is intercepted, it inherits the text/binary attribute specified on the fopen statement. The output to and input from the Debug Tool log file behaves like terminal I/O, with the following considerations:

- Intercepted input behaves as though the terminal was opened for record I/O. Intercepted input is truncated if the data is longer than the record size and the truncated data is not available to subsequent reads.
- Intercepted output is not truncated. Data is split across multiple lines.
- Some situations causing an error with the real file might not cause an error when the file is intercepted (for example, truncation errors do not occur). Files expecting specific error conditions do not make good candidates for interception.
- Only sequential I/O can be performed on an intercepted stream, but file positioning functions are tolerated and the real file position is not changed. fseek, rewind, ftell, fgetpos, and fsetpos do not cause an error, but have no effect.
- The logical record length of an intercepted stream reflects the logical record length of the real file.
- When an unintercepted memory file is opened, the record format is always fixed and the open mode is always binary. These attributes are reflected in the intercepted stream.
- Files opened to the terminal for write are flushed before an input operation occurs from the terminal. This is not supported for intercepted files.

Other characteristics of intercepted files are:

- When an `fclose()` occurs or `INTERCEPT` is set OFF for a file that was intercepted, the data is flushed to the session log file before the file is closed or the `SET INTERCEPT OFF` command is processed.
- When an `fopen()` occurs for an intercepted file, an open occurs on the real file before the interception takes effect. If the `fopen()` fails, no interception occurs for that file and any assumptions about the real file, such as the `ddname` allocation and data set defaults, take effect.
- The behavior of the `ASIS` suboption on the `fopen()` statement is not supported for intercepted files.
- When the `clrmemf()` function is invoked and memory files have been intercepted, the buffers are flushed to the session log file before the files are removed.
- If the `fldata()` function is invoked for an intercepted file, the characteristics of the real file are returned.
- If `stderr` is intercepted, the interception overrides the Language Environment message file (the default destination for `stderr`). A subsequent `SET INTERCEPT OFF` command returns `stderr` to its `MSGFILE` destination.
- If a file is opened with a `ddname`, interception occurs only if the `ddname` is specified on the `INTERCEPT` command. Intercepting the underlying file name does not cause interception of the stream.
- User prefix qualifications are included in MVS data set names entered in the `INTERCEPT` command, using the same rules as defined for the `fopen()` function.
- If library functions are invoked when Debug Tool is waiting for input for an intercepted file (for example, if you interactively enter `fwrite(..)` when Debug Tool is waiting for input), subsequent behavior is undefined.
- I/O intercepts remain in effect for the entire debug session, unless you terminate them by selecting `SET INTERCEPT OFF`.

Command line redirection of the standard streams is supported under Debug Tool, as shown below.

1>&2 If `stderr` is the target of the interception command, `stdout` is also intercepted. If `stdout` is the target of the `INTERCEPT` command, `stderr` is not intercepted. When `INTERCEPT` is set OFF for `stdout`, the stream is redirected to `stderr`.

2>&1 If `stdout` is the target of the `INTERCEPT` command, `stderr` is also intercepted. If `stderr` is the target of the `INTERCEPT` command, `stdout` is not intercepted. When `INTERCEPT` is set OFF for `stderr`, the stream is redirected to `stdout` again.

1>file.name

`stdout` is redirected to **file.name**. For interception of `stdout` to occur, `stdout` or **file.name** can be specified on the interception request. This also applies to **1>>file.name**

2>file.name

`stderr` is redirected to **file.name**. For interception of `stderr` to occur, `stderr` or **file.name** can be specified on the interception request. This also applies to **2>>file.name**

2>&1 1>file.name

`stderr` is redirected to `stdout`, and both are redirected to **file.name**. If **file.name** is specified on the interception command, both `stderr` and `stdout` are intercepted. If you specify `stderr` or `stdout` on the `INTERCEPT` command, the behavior follows rule 1b above.

1>&2 2>file.name

stdout is redirected to stderr, and both are redirected to **file.name**. If you specify **file.name** on the INTERCEPT command, both stderr and stdout are intercepted. If you specify stdout or stderr on the INTERCEPT command, the behavior follows rule 1a above.

The same standard stream cannot be redirected twice on the command line. Interception is undefined if this is violated, as shown below.

2>&1 2>file.name

Behavior of stderr is undefined.

1>&2 1>file.name

Behavior of stdout is undefined.

Refer to the following sections for more information related to the material discussed in this section.

Related references

z/OS C/C++ Programming Guide

Scope of objects in C and C++

An object is *visible* in a block or source file if its data type and declared name are known within the block or source file. The region where an object is visible is referred to as its scope. In Debug Tool, an object can be a variable or function and is also used to refer to line numbers.

Note: The use of an object here is not to be confused with a C++ object. Any reference to C++ will be qualified as such.

In ANSI C, the four kinds of scope are:

- Block
- File
- Function
- Function prototype

For C++, in addition to the scopes defined for C, it also has the class scope.

An object has block scope if its declaration is located inside a block. An object with block scope is visible from the point where it is declared to the closing brace (}) that terminates the block.

An object has file scope if its definition appears outside of any block. Such an object is visible from the point where it is declared to the end of the source file. In Debug Tool, if you are qualified to the compilation unit with the file static variables, file static and global variables are always visible.

The only type of object with function scope is a label name.

An object has function prototype scope if its declaration appears within the list of parameters in a function prototype.

A class member has class scope if its declaration is located inside a class.

You cannot reference objects that are visible at function prototype scope, but you can reference ones that are visible at file or block scope if:

- For C variables and functions, the source file was compiled with `TEST(SYM)` and the object was referenced somewhere within the source.
- For C variables declared in a block that is nested in another block, the source file was compiled with `TEST(SYM, BLOCK)`.
- For line numbers, the source file was compiled with `TEST(LINE) GONUMBER`.
- For labels, the source file was compiled with `TEST(SYM, PATH)`. In some cases (for example, when using `GOTO`), labels can be referenced if the source file was compiled with `TEST(SYM, NOPATH)`.

Debug Tool follows the same scoping rules as ANSI, except that it handles objects at file scope differently. An object at file scope can be referenced from within Debug Tool at any point in the source file, not just from the point in the source file where it is declared. Debug Tool session variables always have a higher scope than program variables, and consequently have higher precedence than a program variable with the same name. The program variable can always be accessed through qualification.

In addition, Debug Tool supports the referencing of variables in multiple load modules. Multiple load modules are managed through the C library functions `dllload()`, `dllfree()`, `fetch()`, and `release()`.

“Example: referencing variables and setting breakpoints in C and C++ blocks” on page 251

Related concepts

“Storage classes in C and C++”

Storage classes in C and C++

Debug Tool supports the change and reference of all objects declared with the following storage classes:

```
auto
register
static
extern
```

Session variables declared during the Debug Tool session are also available for reference and change.

An object with `auto` storage class is available for reference or change in Debug Tool, provided the block where it is defined is active. Once a block finishes executing, the `auto` variables within this block are no longer available for change, but can still be examined using `DESCRIBE ATTRIBUTES`.

An object with `register` storage class might be available for reference or change in Debug Tool, provided the variable has not been optimized to a register.

An object with `static` storage class is always available for change or reference in Debug Tool. If it is not located in the currently qualified compile unit, you must specifically qualify it.

An object with `extern` storage class is always available for change or reference in Debug Tool. It might also be possible to reference such a variable in a program even if it is not defined or referenced from within this source file. This is possible provided Debug Tool can locate another compile unit (compiled with `TEST(SYM)`) with the appropriate definition.

Blocks and block identifiers for C

It is often necessary to set breakpoints on entry into or exit from a given block or to reference variables that are not immediately visible from the current block. Debug Tool can do this, provided that all blocks are named. It uses the following naming convention:

- The outermost block of a function has the same name as the function.
- Blocks enclosed in this outermost block are sequentially named: %BLOCK2, %BLOCK3, %BLOCK4, and so on in order of their appearance in the function.

When these block names are used in the Debug Tool commands, you might need to distinguish between nested blocks in different functions within the same source file. This can be done by naming the blocks in one of two ways:

Short form

function_name:>%BLOCKzzz

Long form

function_name:>%BLOCKxxx :>%BLOCKyyy: ... :>%BLOCKzzz

%BLOCKzzz is contained in %BLOCKyyy, which is contained in %BLOCKxxx. The short form is always allowed; it is never necessary to specify the long form.

The currently active block name can be retrieved from the Debug Tool variable %BLOCK. You can display the names of blocks by entering:

```
DESCRIBE CU;
```

Blocks and block identifiers for C++

Block Identifiers tend to be longer for C++ than C because C++ functions can be overloaded. In order to distinguish one function name from the other, each block identifier is like a prototype. For example, a function named shapes(int,int) in C would have a block named shapes; however, in C++ the block would be called shapes(int,int).

You must always refer to a C++ block identifier in its entirety, even if the function is not overloaded. That is, you cannot refer to shapes(int,int) as shapes only.

Note: The block name for main() is always main (without the qualifying parameters after it) even when compiled with C++ because main() has extern C linkage.

Since block names can be quite long, it is not unusual to see the name truncated in the LOCATION field on the first line of the screen. If you want to find out where you are, enter:

```
QUERY LOCATION
```

and the name will be shown in its entirety (wrapped) in the session log.

Block identifiers are restricted to a length of 255 characters. Any name longer than 255 characters is truncated.

Example: referencing variables and setting breakpoints in C and C++ blocks

The program below is used as the basis for several examples, described after the program listing.

```
#pragma runopts(EXECOPS)
#include <stdlib.h>

main()
{
    >>> Debug Tool is given <<<
    >>> control here.    <<<
    init();
    sort();
}

short length = 40;
static long *table;

init()
{
    table = malloc(sizeof(long)*length);
    :
}

sort ()
{
    /* Block sort */
    int i;
    for (i = 0; i < length-1; i++) {    /* Block %BLOCK2 */
        int j;
        for (j = i+1; j < length; j++) { /* Block %BLOCK3 */
            static int temp;
            temp = table[i];
            table[i] = table[j];
            table[j] = temp;
        }
    }
}
```

Scope and visibility of objects

Let's assume the program shown above is compiled with TEST(SYM). When Debug Tool gains control, the file scope variables `length` and `table` are available for change, as in:

```
length = 60;
```

The block scope variables `i`, `j`, and `temp` are not visible in this scope and cannot be directly referenced from within Debug Tool at this time. You can list the line numbers in the current scope by entering:

```
LIST LINE NUMBERS;
```

Now let's assume the program is compiled with TEST(SYM, NOBLOCK). Since the program is explicitly compiled using NOBLOCK, Debug Tool will never know about the variables `j` and `temp` because they are defined in a block that is nested in another block. Debug Tool does know about the variable `i` since it is not in a scope that is nested.

Blocks and block identifiers

In the program above, the function `sort` has three blocks:

```
sort
```

```
%BLOCK2
%BLOCK3
```

The following example sets a breakpoint on entry to the second block of sort:

```
at entry sort:>%BLOCK2;
```

The following example sets a breakpoint on exit of the first block of main and lists the entries of the sorted table.

```
at exit main {
    for (i = 0; i < length; i++)
        printf("table entry %d is %d\n", i, table[i]);
}
```

The following example lists the variable temp in the third block of sort. This is possible since temp has the static storage class.

```
LIST sort:>%BLOCK3:temp;
```

Displaying environmental information

You can also use the DESCRIBE command to display a list of attributes applicable to the current run-time environment. The type of information displayed varies from language to language.

Issuing DESCRIBE ENVIRONMENT displays a list of open files and conditions being monitored by the run-time environment. For example, if you enter DESCRIBE ENVIRONMENT while debugging a C or C++ program, you might get the following output:

```
Currently open files
    stdout
    sysprint
The following conditions are enabled:
    SIGFPE
    SIGILL
    SIGSEGV
    SIGTERM
    SIGINT
    SIGABRT
    SIGUSR1
    SIGUSR2
    SIGABND
```

Qualifying variables and changing the point of view in C and C++

Qualification is a method of:

- Specifying an object through the use of qualifiers
- Changing the point of view

Qualification is often necessary due to name conflicts, or when a program consists of multiple load modules, compile units, and/or functions.

When program execution is suspended and Debug Tool receives control, the default, or *implicit* qualification is the active block at the point of program suspension. All objects visible to the C or C++ program in this block are also visible to Debug Tool. Such objects can be specified in commands without the use of qualifiers. All others must be specified using *explicit qualification*.

Qualifiers depend, of course, upon the naming convention of the system where you are working.

“Example: using qualification in C” on page 254

Related tasks

“Qualifying variables in C and C++”

“Changing the point of view in C and C++”

Qualifying variables in C and C++

You can precisely specify an object, provided you know the following:

- Load module or DLL name
- Source file (compilation unit) name
- Block name (must include function prototype for C++ block qualification).

These are known as qualifiers and some, or all, might be required when referencing an object in a command. Qualifiers are separated by a combination of greater than signs (>) and colons and precede the object they qualify. For example, the following is a fully qualified object:

```
load_name::>cu_name:>block_name:>object
```

If required, *load_name* is the name of the load module. It is required only when the program consists of multiple load modules and when you want to change the qualification to other than the current load module. *load_name* is enclosed in double quotation marks. If it is not, it must be a valid identifier in the C or C++ programming language. *load_name* can also be the Debug Tool variable %LOAD.

If required, *CU_NAME* is the name of the compilation unit or source file. The *cu_name* must be the fully qualified source file name or an absolute pathname. It is required only when you want to change the qualification to other than the currently qualified compilation unit. It can be the Debug Tool variable %CU. If there appears to be an ambiguity between the compilation unit name, and (for example), a block name, you must enclose the compilation unit name in double quotation marks ("").

If required, *block_name* is the name of the block. *block_name* can be the Debug Tool variable %BLOCK.

“Example: using qualification in C” on page 254

Refer to the following sections for more information related to the material discussed in this section.

Related concepts

“Blocks and block identifiers for C” on page 250

Changing the point of view in C and C++

To change the point of view from the command line or a command file, use qualifiers in conjunction with the SET QUALIFY command. This can be necessary to get to data that is inaccessible from the current point of view, or can simplify debugging when a number of objects are being referenced.

It is possible to change the point of view to another load module or DLL, to another compilation unit, to a nested block, or to a block that is not nested. The SET keyword is optional.

“Example: using qualification in C” on page 254

Example: using qualification in C

The examples below use the following program.

```
LOAD MODULE NAME:  MAINMOD
SOURCE FILE  NAME:  MVSID.SORTMAIN.C
```

```
short length = 40;
main ()
{
    long *table;
    void (*pf)();

    table = malloc(sizeof(long)*length);
    :
    pf = fetch("SORTMOD");
    (*pf)(table);
    :
    release(pf);
    :
}
```

```
LOAD MODULE NAME:  SORTMOD
SOURCE FILE  NAME:  MVSID.SORTSUB.C
```

```
short length = 40;
short sn = 3;
void (long table[])
{
    short i;
    for (i = 0; i < length-1; i++) {
        short j;
        for (j = i+1; j < length; j++) {
            float sn = 3.0;
            short temp;
            temp = table[i];
            :
            >>> Debug Tool is given <<<
            >>> control here.    <<<
            :
            table[i] = table[j];
            table[j] = temp;
        }
    }
}
```

When Debug Tool receives control, variables *i*, *j*, *temp*, *table*, and *length* can be specified without qualifiers in a command. If variable *sn* is referenced, Debug Tool uses the variable that is a float. However, the names of the blocks and compile units differ, maintaining compatibility with the operating system.

Qualifying variables

- Change the file scope variable *length* defined in the compilation unit *MVSID.SORTSUB.C* in the load module *SORTMOD*:
"SORTMOD":>"MVSID.SORTSUB.C":>length = 20;
- Assume Debug Tool gained control from *main()*. The following changes the variable *length*:

```
%LOAD:>"MVSID.SORTMAIN.C":>length = 20;
```

Because *length* is in the current load module and compilation unit, it can also be changed by:

```
length = 20;
```

- Assume Debug Tool gained control as shown in the example program above. You can break whenever the variable `temp` in load module `SORTMOD` changes in any of the following ways:

```
AT CHANGE temp;
AT CHANGE %BLOCK3:>temp;
AT CHANGE sort:%BLOCK3:>temp;
AT CHANGE %BLOCK:>temp;
AT CHANGE %CU:>sort:>%BLOCK3:>temp;
AT CHANGE "MVSID.SORTSUB.C":>sort:>%BLOCK3:>temp;
AT CHANGE "SORTMOD"::>"MVSID.SORTSUB.C":>sort:>%BLOCK3:>temp;
```

Changing the point of view

- Qualify to the second nested block in the function `sort()` in `sort`.
`SET QUALIFY BLOCK %BLOCK2;`

You can do this in a number of other ways, including:

```
QUALIFY BLOCK sort:>%BLOCK2;
```

Once the point of view changes, Debug Tool has access to objects accessible from this point of view. You can specify these objects in commands without qualifiers, as in:

```
j = 3;
temp = 4;
```

- Qualify to the function `main` in the load module `MAINMOD` in the compilation unit `MVSID.SORTMAIN.C` and list the entries of `table`.

```
QUALIFY BLOCK "MAINMOD"::>"MVSID.SORTMAIN.C":>main;
LIST table[i];
```

Stepping through C++ programs

You can step through methods as objects are constructed and destructed. In addition, you can step through static constructors and destructors. These are methods of objects that are executed before and after `main()` respectively.

If you are debugging a program that calls a function that resides in a header file, the cursor moves to the applicable header file. You can then view the function source as you step through it. Once the function returns, debugging continues at the line following the original function call.

You can step around a header file function by issuing the `STEP OVER` command. This is useful in stepping over Library functions (for example, string functions defined in `string.h`) that you cannot debug anyway.

Setting breakpoints in C++

The differences between setting breakpoints in C++ and C are described below.

Setting breakpoints in C++ using `AT ENTRY/EXIT`

`AT ENTRY/EXIT` sets a breakpoint in the specified block. You can set a breakpoint on methods, methods within nested classes, templates, and overloaded operators. An example is given for each below.

A block identifier can be quite long, especially with templates, nested classes, or class with many levels of inheritance. In fact, it might not even be obvious at first as to the block name for a particular function. To set a breakpoint for these

nontrivial blocks can be quite cumbersome. Therefore, it is recommended that you make use of DESCRIBE CU and retrieve the block identifier from the session log.

When you do a DESCRIBE CU, the methods are always shown qualified by their class. If a method is unique, you can set a breakpoint by using just the method name. Otherwise, you must qualify the method with its class name. The following two examples are equivalent:

```
AT ENTRY method()
```

```
AT ENTRY classname::method()
```

The following examples are valid:

```
AT ENTRY square(int,int)
```

```
AT ENTRY shapes::square(int)
```

```
AT EXIT outer::inner::func()
```

```
AT EXIT Stack<int,5>::Stack()
```

```
AT ENTRY Plus::operator++(int)
```

```
AT ENTRY ::fail()
```

'simple' method square

Method square qualified by its class shapes.

Nested classes. Outer and inner are classes. func() is within class inner.

Templates.

Overloaded operator.

Functions defined at file scope must be referenced by the global scope operator ::

The following examples are invalid:

```
AT ENTRY shapes
```

```
AT ENTRY shapes::square
```

```
AT ENTRY shapes:>square(int)
```

Where shapes is a class. Cannot set breakpoint on a class. (There is no block identifier for a class.)

Invalid since method square must be followed by its parameter list.

Invalid since shapes is a class name, not a block name.

Setting breakpoints in C++ using AT CALL

AT CALL gives Debug Tool control when the application code attempts to call the specified entry point. The entry name must be a fully qualified name. That is, the name shown in DESCRIBE CU must be used. Using the example

```
AT ENTRY shapes::square(int)
```

to set a breakpoint on the method square, you must enter:

```
AT CALL shapes::square(int)
```

even if square is uniquely identified.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Retrieving commands from the Log and Source windows” on page 118

Examining C++ objects

When displaying an C++ object, only the local member variables are shown. Access types (public, private, protected) are not distinguished among the variables. The member functions are not displayed. If you want to see their attributes, you can display them individually, but not in the context of a class. When displaying a derived class, the base class within it is shown as type class and will not be expanded.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Example: displaying attributes of C++ objects”

Example: displaying attributes of C++ objects

The examples below use the following definitions.

```
class shape { ... };

class line : public shape {
    member variables of class line...
}

line edge;
```

Displaying object attributes

To describe the attributes of the object edge, enter the following command.

```
DESCRIBE ATTRIBUTES edge;
```

The Log window displays the following output.

```
DESCRIBE ATTRIBUTES edge;
ATTRIBUTES for edge
  Its address is yyyyyyyy and its length is xx
  class line
    class shape
      member variables of class shape....
```

Note that the base class is shown as class shape _shape.

Displaying class attributes

To display the attributes of class shape, enter the following command.

```
DESCRIBE ATTRIBUTES class shape;
```

The Log window displays the following output.

```
DESCRIBE ATTRIBUTES class shape ;
ATTRIBUTES for class shape
  const class shape...
```

Displaying static data

If a class contains static data, the static data will be shown as part of the class when displayed. For example:

```
class A {
    int x;
    static int y;
}

A obj;
```


You can also display the static member by referencing it as `A::y` since each object of class A has the same value.

Displaying global data

To avoid ambiguity, variables declared at file scope can be referenced using the global scope operator `::`. For example:

```
int x;
class A {
    int x;
    :
    }
}
```

If you are within a member function of A and want to display the value of x at file scope, enter `LIST ::x`. If you do not use `::`, entering `LIST x` will display the value of x for the current object (i.e., `this->x`).

Monitoring storage in C++

You might find it useful to monitor registers (general-purpose and floating-point) while stepping through your code and assembly listing by using the `LIST REGISTERS` command. The compiler listing displays the pseudo assembly code, including Debug Tool hooks. You can watch the hooks that you stop on and watch expected changes in register values step by step in accordance with the pseudo assembly instructions between the hooks. You can also modify the value of machine registers while stepping through your code.

You can list the contents of storage in various ways. Using the `LIST REGISTERS` command, you can receive a list of the contents of the general-purpose registers or the floating-point registers.

You can also monitor the contents of storage by specifying a dump-format display of storage. To accomplish this, use the `LIST STORAGE` command. You can specify the address of the storage that you want to view, as well as the number of bytes.

Example: monitoring and modifying registers and storage in C

The examples below use the following C program to demonstrate how to monitor and modify registers and storage.

```
int dbl(int j)          /* line 1 */
{                      /* line 2 */
    return 2*j;         /* line 3 */
}                      /* line 4 */
int main(void)
{
    int i;
    i = 10;
    return dbl(i);
}
```

If you compile the program above using the compiler options `TEST(ALL),LIST`, then your pseudo assembly listing will be similar to the listing shown below.

```
* int dbl(int j)
*      ST    r1,152(,r13)
* {
*      EX    r0,H00K..PGM-ENTRY
*      return 2*j;
*      EX    r0,H00K..STMT
*      L     r15,152(,r13)
```

```

                                L    r15,0(,r15)
                                SLL  r15,1
                                B    @5L2
                                DC    A@5L2-ep)
                                NOPR
@5L1                            DS    0D
*    }
@5L2                            DS    0D
                                EX    r0,H00K..PGM-EXIT

```

To display a continuously updated view of the registers in the Monitor window, enter the following command:

```
MONITOR LIST REGISTERS
```

After a few steps, Debug Tool halts on line 1 (the program entry hook, shown in the listing above). Another STEP takes you to line 3, and halts on the statement hook. The next STEP takes you to line 4, and halts on the program exit hook. As indicated by the pseudo assembly listing, only register 15 has changed during this STEP, and it contains the return value of the function. In the Monitor window, register 15 now has the value 0x00000014 (decimal 20), as expected.

You can change the value from 20 to 8 just before returning from `dbl()` by issuing the command:

```
%GPR15 = 8 ;
```

Chapter 35. Debugging an assembler program

To debug programs that have been assembled with debug information, you can use most of the Debug Tool commands. Any exceptions are noted in *Debug Tool for z/OS Reference and Messages*. Before debugging an assembler program, prepare your program as described in Chapter 10, “Preparing an assembler program,” on page 45.

The SET ASSEMBLER and SET DISASSEMBLY commands

The SET ASSEMBLER ON and SET DISASSEMBLY ON commands enable some of the same functions. However, you must consider which type of CUs that you will be debugging (assembler, disassembly, or both) before deciding which command to use. The following guidelines can help you decide which command to use:

- If you are debugging assembler CUs but no disassembly CUs, you might want to use the SET ASSEMBLER ON command. If you need the following functions, use the SET ASSEMBLER ON command:
 - Use the LIST, LIST NAMES CUS, or DESCRIBE CUS commands to see the name of disassembly CUs.
 - Use AT APPEARANCE to stop Debug Tool when the disassembly CU is loaded.

If you don’t need any of these functions, you don’t need to use either command.

- If you are debugging a disassembly CU, you must use the SET DISASSEMBLY ON command so that you can see the disassembly view of the disassembly CUs. The SET DISASSEMBLY ON command enables the functions enabled by SET ASSEMBLER ON and also enables the following functions that are not available through the SET ASSEMBLER ON command:
 - View the disassembled listing in the Source window.
 - Use the STEP INTO command to enter the disassembly CU.
 - Use the AT ENTRY * command to stop at the entry point of disassembly CUs.

If you are debugging an assembler CU and later decide you want to debug a disassembly CU, you can enter the SET DISASSEMBLY ON command after you enter the SET ASSEMBLER ON command.

Loading an assembler program’s debug information

Use the LOADDEBUGDATA (or LDD) command to indicate to Debug Tool that a compile unit is an assembler compile unit and to load the debug information associated with that compile unit. The LDD command can be issued only for compile units which have no debug information and are, therefore, considered disassembly compile units. In the following example, mypgm is the compile unit (CSECT) name of an assembler program:

```
LDD mypgm
```

Debug Tool locates the debug information in a data set with the following name: *yourid.EQALANGX(mypgm)*. If Debug Tool finds this data set, you can begin to debug your assembler program. Otherwise, enter the SET SOURCE or SET DEFAULT LISTINGS command to indicate to Debug Tool where to find the debug information. In remote debug mode, the remote debugger prompts you for the data set information when the program is stepped into.

Normally, compile units without debug information are not listed when you enter the DESCRIBE CUS or LIST NAMES CUS commands. To include these compile units, enter the SET ASSEMBLER ON command. The next time you enter the DESCRIBE CUS or LIST NAMES CUS command, these compile units are listed.

Debug Tool session panel while debugging an assembler program

The Debug Tool session panel below shows the information displayed in the Source window while you debug an assembler program.

```

Assemble LOCATION: PUBS :> 34.1
Command ==>
MONITOR ---1---2---3---4---5---6---7---8---9---10--- LINE: 0 OF 0
***** TOP OF MONITOR *****
***** BOTTOM OF MONITOR *****

SOURCE: PUBS +---1---2---3---4---5---6---7---8---9---10-- LINE: 60 OF 513

 1 34      2      *      5
34 00000078 OPENIT EQU *
34 00000078 + OPEN ((2),INPUT)
34      3      + CNOP 0,4
34 00000078 4510 B080 + BAL 1,++8
35 0000007C + DC A(0)
36 00000080 5021 0000 + ST 2,0(1,0)
37 00000084 9280 1000 + MVI 0(1),128
38 00000088 0A13 + SVC 19
39      4      CALL CEEMOUT,(STRING,DEST,0),VL
39 + SYSSTATE TEST
39 + CNOP 0,4

LOG 0---1---2---3---4---5---6---7---8---9---10---1 LINE: 1 OF 9
***** TOP OF LOG *****
0001 IBM Debug Tool Version 5 Release 1 Mod 0
0002 10/13/2004 10:20:27 AM
0003 5655-M18 and 5655-M19: (C) Copyright IBM Corp. 1992, 2004
0004 EQA1872E An error occurred while opening file: INSPREF. The file may not exist, or is not accessible.
0005 Source or Listing data is not available, or the CU was not compiled with the correct compile options.
0006 LDD PUBS ;
0007 SET DEFAULT SCROLL CSR ;
0008 AT 34 ;
0009 GO ;
***** BOTTOM OF LOG *****
PF 1:?      2:STEP      3:QUIT      4:LIST      5:FIND      6:AT/CLEAR
PF 7:UP      8:DOWN      9:GO       10:ZOOM     11:ZOOM LOG  12:RETRIEVE

```

The information displayed in the Source window is similar to the listing generated by the assembler. The Source window displays the following information:

1 statement number

The statement number is a number assigned by the EQALANGX program. Use this column to set breakpoints and identify statements.

The same statement number can sometimes be assigned to more than one line. Comments, labels and macro invocations are assigned the same statement number as the machine instruction that follows these statements. All of these statements have the same offset within the CSECT, which allows you to put the cursor on any of these lines and press PF6 to set a breakpoint. When the statement is reached, the focus is set on the first line within the statement that contains either a macro invocation or a machine instruction.

2 offset

The offset from the start of the CSECT. This column matches the left-most column in the assembler listing.

3 object

The object code for instructions. This column matches the "Object Code" column in the assembler listing. Object code for data fields is not displayed.

4 macro generated

A "+" in this column indicates that the line is generated by macro expansion.

5 source statement

The original source statement. This column corresponds to the "Source Statement" column in the assembler listing.

%PATHCODE values for assembler programs

This table shows the possible values for the Debug Tool %PATHCODE variable when the current programming language is Assembler:

%PATHCODE	Entry type	Instruction	Additional requirements or comments
1	A block has been entered.	Any	External symbol whose offset corresponds to an instruction
2	A block is about to be exited.	BR R14 (07FE)	These instructions are considered an Exit only if this instruction is not followed by an valid instruction.
		BALR R14,R15 (05EF)	
		BASR R14,R15 (0DEF)	
		BASSM R14,R15 (0CEF)	
		BCR 15,x (07Fx)	
3	Control has reached a label coded in the program.	Any	Label whose offset corresponds to an instruction.

%PATHCODE	Entry type	Instruction	Additional requirements or comments
4	Control is being transferred as a result of a CALL.	BALR R14,R15 (05EF)	
		BASR R14,R15 (0DEF)	
		BASSM R14,R15 (0CEF)	
		SVC (0A)	
		PC (B218)	
		BAL (45)	Except BAL 1,xxx is not considered a CALL
		BAS (4D)	
		BALR x,y (05)	
		BASR x,y (0D)	
		BASSM x,y (0C)	
		BRAS (A7x5)	
		BRASL (C0x5)	
5	Control is returning from a CALL.	Statement after CALL	If the statement after a CALL is an instruction, it gets an entry here.
6	A conditional branch is about to be executed.	BC x (47x)	$x \neq 15 \ \& \ X \neq 0$
		BCR x (07x)	$x \neq 15 \ \& \ X \neq 0$
		BCT (46)	
		BCTR (06)	
		BCTGR (B946)	
		BXH (86)	
		BXHG (EB44)	
		BXLE (87)	
		BXLEG (EB45)	
		BRC x (A7x4)	$x \neq 15 \ \& \ X \neq 0$
		BRCL (C0x4)	
		BRCT (A7x6)	
		BRCTG (A7x7)	
		BRXH (84)	
		BRXHG (EC44)	
		BRXLE (85)	
		BRXLG (EC45)	

%PATHCODE	Entry type	Instruction	Additional requirements or comments
7	A conditional branch was not executed and control has "fallen-through" to the next instruction.	Statement after Conditional Branch	
8	An unconditional branch is about to be executed.	BC 15,x (47Fx)	
		BRC 15,x (A7F4)	
		BRCL 15,x (C0F4)	
		BSM (0B)	

Restrictions for debugging an assembler program

When you debug assembler programs the following general restrictions apply:

- Only application programs are supported. No support is provided for debugging system routines, authorized programs, CICS exits, and so on.
- No support is provided for debugging subtasks. If an ATTACH is run, the debugger always follows the parent task.
- Debugging of programs that do not use non-standard linkage conventions for registers 13, 14, and 15 or that use the Linkage Stack is not supported. This can cause the following commands to function incorrectly:
 - LIST CALLS
 - STEP RETURN
 - STEP (when stopped at a return instruction)
 - %EPA
- Debugging of programs that use the MVS XCTL SVC is not supported.
- Debugging of programs that use 64-bit addressing is not supported.
- Debugging of programs that use Access Register mode is not supported.
- If you are debugging a program that uses ESTAE or ESTAEX, the program behaves as if TRAP(0FF) were specified for all Abends while the ESTAE or ESTAEX is active, except program checks. In other words, no condition is seen by Debug Tool. Any Abends except program checks are handled by the ESTAE(X) exit in your program.
- If you are debugging a program that uses SPIE or ESPIE, the program behaves as if TRAP(0FF) were specified for all program checks while the SPIE or ESPIE is active, except a program check that might arise from the use of the CALL Debug Tool command.
- The debugging of TSO Command Processors is not supported.
- If you start debugging in a load module that is not the "top" load module, you cannot continue debugging after that load module returns to its caller.

Restrictions for debugging a Language Environment assembler MAIN program

When you debug a Language Environment-enabled assembler main program, the following restrictions apply:

- If Debug Tool is positioned at the entry point to the assembler main program and you enter a STEP command, the STEP command stops at the instruction that is after the prologue BALR instruction that initializes Language Environment. You cannot step through the portion of the prologue that is prior to the completion of Language Environment initialization.
- If you set a breakpoint in the prologue prior to the completion of Language Environment initialization, the breakpoint is accepted. However, Debug Tool does not stop or gain control at this breakpoint.
- There is no support for debugging Language Environment-enabled assembler MAIN programs by using Debug Tool under CICS because of the current restriction between CICS and Language Environment that prohibits running Language Environment-enabled assembler MAIN programs under CICS.

Restrictions on setting breakpoints in the prologue of Language Environment assembler programs

The following restrictions apply when you attempt to set explicit or implicit breakpoints in the prologue of a Language Environment assembler program:

- If you try to step across the portion of the prologue code that is between the point where the stack extend routine is called and the LR 13,x instruction that loads the address of the new DSA into register 13, the STEP command stops at the instruction immediately following the LR 13,x instruction.
- If you try to set a breakpoint in the portion of the prologue code between the point where the stack extend routine is called and the LR 13,x instruction that loads the address of the new DSA into register 13, Debug Tool will not set the breakpoint.

Restrictions for debugging non-Language Environment programs

If you specify the TEST run-time option with the NOPROMPT suboption when you start your program and Debug Tool is subsequently started by CALL CEETEST or the raising of an Language Environment condition, you can debug both Language Environment and non-Language Environment programs and detect both Language Environment and non-Language Environment events in the enclave that started Debug Tool and in subsequent enclaves. You cannot debug non-Language Environment programs or detect non-Language Environment events in higher-level enclaves. After control has returned from the enclave in which Debug Tool was started, you can no longer debug non-Language Environment programs or detect non-Language Environment events.

Restrictions for debugging self-modifying code

Debug Tool cannot debug self-modifying code. If your program contains self-modifying code that modifies an instruction while the containing compilation unit is being debugged, the result can be unpredictable, including an abnormal termination (ABEND) of Debug Tool. If your program contains self-modifying code that completely replaces an instruction while the containing compilation unit is being debugged, the result might not be an ABEND. However, Debug Tool might miss a breakpoint on that instruction or display a message indicating an invalid hook address at delete.

The following coding techniques can be used to minimize problems debugging self-modifying code:

1. Do not modify part of an instruction. Instead, replace an instruction. The following table compares coding techniques:

Coding that modifies an instructions	Coding that replaces an instruction
<pre>ModInst BC 0,Target ... MVI ModInst+1,X'F0'</pre>	<pre>ModInst BC 0,Target ... MVC ModInst(4),NewInst ... NewInst BC 15,Target</pre>

2. Define instructions to be modified by using DC instructions instead of executable instructions. For example, use the instruction `ModInst DC X'4700',S(Target)` instead of the instruction `MVC ModInst(4),NewInst`.

Chapter 36. Debugging a disassembled program

To debug programs that have been compiled or assembled without debug information, you can use the disassembly view. When you use the disassembly view, symbolic information from the original source program (program variables, labels, and other symbolic references to a section of memory) is not available. The DYNDEBUG switch must be ON before you use the disassembly view.

If you are not familiar with the program that you are debugging, we recommend that you have a copy of the listing that was created by the compiler or High Level Assembler (HLASM) available while you debug the program. There are no special assembly or compile requirements that the program must comply with to use the disassembly view.

The SET ASSEMBLER and SET DISASSEMBLY commands

The SET ASSEMBLER ON and SET DISASSEMBLY ON commands enable some of the same functions. However, you must consider which type of CUs that you will be debugging (assembler, disassembly, or both) before deciding which command to use. The following guidelines can help you decide which command to use:

- If you are debugging assembler CUs but no disassembly CUs, you might want to use the SET ASSEMBLER ON command. If you need the following functions, use the SET ASSEMBLER ON command:
 - Use the LIST, LIST NAMES CUS, or DESCRIBE CUS commands to see the name of disassembly CUs.
 - Use AT APPEARANCE to stop Debug Tool when the disassembly CU is loaded.

If you don't need any of these functions, you don't need to use either command.

- If you are debugging a disassembly CU, you must use the SET DISASSEMBLY ON command so that you can see the disassembly view of the disassembly CUs. The SET DISASSEMBLY ON command enables the functions enabled by SET ASSEMBLER ON and also enables the following functions that are not available through the SET ASSEMBLER ON command:
 - View the disassembled listing in the Source window.
 - Use the STEP INTO command to enter the disassembly CU.
 - Use the AT ENTRY * command to stop at the entry point of disassembly CUs.

If you are debugging an assembler CU and later decide you want to debug a disassembly CU, you can enter the SET DISASSEMBLY ON command after you enter the SET ASSEMBLER ON command.

Capabilities of the disassembly view

When you use the disassembly view, you can do the following tasks:

- Set breakpoints at the start of any assembler instruction.
- Step through the disassembly instructions of your program.
- Display and modify registers.
- Display and modify storage.
- Monitor general-purpose registers or areas of main storage.
- Switch the debug view.

- Use most Debug Tool commands.

Starting the disassembly view

To start the disassembly view:

1. Enter the SET DISASSEMBLY ON command
2. Open the program that does not contain debug data. Debug Tool then changes the language setting to **Disassem** and the Source window displays the assembler code.

If you enter a program that does contain debug data, the language setting does not change and the Source window does not display disassembly code.

The disassembly view

When you debug a program through the disassembly view, the Source window displays the disassembly instructions. The language area of the Debug Tool screen (upper left corner) displays the word **Disassem**. The Debug Tool screen appears as follows:

```

Disassem LOCATION: MAIN initialization
Command ==> Scroll ==> PAGE
MONITOR --+----1-----2-----3-----4-----5-----6 LINE: 0 OF 0
***** TOP OF MONITOR *****
***** BOTTOM OF MONITOR *****

SOURCE: MAIN +----1-----2-----3-----4-----5-----+ LINE: 1 OF 160
  0 1950C770 47F0 F014 BC 15,20(,R15) .
  A 4 1950C774 00C3 ???? .
  6 1950C776 B C5C5 ???? .
  8 1950C778 0000 ???? .
  A 1950C77A 0080 C ???? .
  C 1950C77C 0000 ???? .
  E 1950C77E 00C4 ???? D .
 10 1950C780 47F0 F001 BC 15,1(,R15) .
 14 1950C784 90EC D00C STM R14,R12,12(R13) .
 18 1950C788 18BF LR R11,R15 E .
 1A 1950C78A 5820 B130 L R2,304(,R11) .
 1E 1950C78E 58F0 B134 L R15,308(,R11) .
 22 1950C792 05EF BALR R14,R15 .
 24 1950C794 1821 LR R2,R1 .
 26 1950C796 58E0 C2F0 L R14,752(,R12) .
 2A 1950C79A 9680 E008 OI 8(R14),128 .
 2E 1950C79E 05B0 BALR R11,0 .
LOG 0-----1-----2-----3-----4-----5-----6- LINE: 1 OF 5
***** TOP OF LOG *****
0001 IBM Debug Tool Version 5 Release 1 Mod 0
0002 09/26/2004 10:52:22 AM
0003 5655-M18 and 5655-M19: (C) Copyright IBM Corp. 1992, 2004
0004 EQA1872E An error occurred while opening file: INSPREF. The file may not
0005 exist, or is not accessible.
0006 SET DISASSEMBLY ON ;
PF 1:? 2:STEP 3:QUIT 4:LIST 5:FIND 6:AT/CLEAR
PF 7:UP 8:DOWN 9:GO 10:ZOOM 11:ZOOM LOG 12:RETRIEVE

```

A Prefix Area

Displays the offset from the start of the CU or CSECT.

B Columns 1-8

Displays the address of the machine instruction in memory.

C Columns 13-26

Displays the machine instruction in memory.

D Columns 29-32

Displays the op-code mnemonic or ???? if the op-code is not valid.

E Columns 35-70

Displays the disassembled machine instruction.

When you use the disassembly view, the disassembly instructions displayed in the source area are not guaranteed to be accurate because it is not always possible to distinguish data from instructions. Because of the possible inaccuracies, we recommend that you have a copy of the listing that was created by the compiler or by HLASM. Debug Tool keeps the disassembly view as accurate as possible by refreshing the Source window whenever it processes the machine code, for example, after a STEP command.

Performing single-step operations

Use the STEP command to single-step through your program. In the disassembly view, you step from one disassembly instruction to the next. Debug Tool highlights the instruction that it runs next.

If you try to step back into the program that called your program, set a breakpoint at the instruction to which you return in the calling program. If you try to step over another program, set a breakpoint immediately after the instruction that calls another program. When you try to step out of your program, Debug Tool displays a warning message and lets you set the appropriate breakpoints. Then you can do the step.

Debug Tool refreshes the disassembly view whenever it determines that the disassembly instructions that are displayed are no longer correct. This refresh can happen while you are stepping through your program.

Setting breakpoints

You can use a special breakpoint when you debug your program through the disassembly view. AT OFFSET sets a breakpoint at the point that is calculated from the start of the entry point address of the CSECT. You can set a breakpoint by entering the AT OFFSET command on the command line or by placing the cursor in the prefix area of the line where you want to set a breakpoint and press the AT function key or type AT in the prefix area.

Debug Tool lets you set breakpoints anywhere within the starting and ending address range of the CU or CSECT as long as the address appears to be a valid op-code and is an even number offset. To avoid setting breakpoints at the wrong offset, we recommend that you verify the offset by referring to a copy of the listing that was created by the compiler or by HLASM.

Restrictions for debugging self-modifying code

Debug Tool cannot debug self-modifying code. If your program contains self-modifying code that modifies an instruction while the containing compilation unit is being debugged, the result can be unpredictable, including an abnormal termination (ABEND) of Debug Tool. If your program contains self-modifying code that completely replaces an instruction while the containing compilation unit is being debugged, the result might not be an ABEND. However, Debug Tool might miss a breakpoint on that instruction or display a message indicating an invalid hook address at delete.

The following coding techniques can be used to minimize problems debugging self-modifying code:

1. Do not modify part of an instruction. Instead, replace an instruction. The following table compares coding techniques:

Coding that modifies an instructions	Coding that replaces an instruction
ModInst BC 0,Target ... MVI ModInst+1,X'F0'	ModInst BC 0,Target ... MVC ModInst(4),NewInst ... NewInst BC 15,Target

2. Define instructions to be modified by using DC instructions instead of executable instructions. For example, use the instruction ModInst DC X'4700',S(Target) instead of the instruction MVC ModInst(4),NewInst.

Displaying and modifying registers

You can display the contents of all the registers by using the LIST REGISTERS command. To display the contents of an individual register, use the LIST Rx command, where x is the individual register number. You can also display the contents of an individual register by placing the cursor on the register and pressing the LIST function key. The default LIST function key is PF4. You can modify the contents of a register by using the assembler assignment statement.

Displaying and modifying storage

You can display the contents of storage by using the LIST STORAGE command. You can modify the contents of storage by using the STORAGE command.

You can also use assembler statements to display and modify storage. For example, to set the four bytes located by the address in register 2 to zero, enter the following command:

```
R2-> <4>=0
```

To verify that the four bytes are set to zero, enter the following command:

```
LIST R2->
```

Changing the program displayed in the disassembly view

You can use the SET QUALIFY command to change the program that is displayed in the disassembly view. Suppose you are debugging program ABC and you need to set a breakpoint in program BCD.

1. Enter the command SET QUALIFY CU BCD on the command line. Debug Tool changes the Source window to display the disassembly instructions for program BCD.
2. Scroll through the Source window until you find the instruction where want to set a breakpoint.
3. To return to program ABC, at the point where the next instruction is to run, issue the SET QUALIFY RESET command.

Restrictions for the disassembly view

When you debug a disassembled program, the following restrictions apply:

- Applications that use the Language Environment XPLINK linking convention are not supported.
- The Dynamic Debug facility must be activated before you start debugging through the disassembly view.

When you debug a program through the disassembly view, Debug Tool cannot stop the application in any of the following situations:

- The program does not comply with the first three restrictions that are listed above.
- Between the following instructions:
 - After the LE stack extend has been called in the prologue code, and
 - Before R13 has been set with a savearea or DSA address and the backward pointer has been properly set.

The application runs until Debug Tool encounters a valid save area backchain.

Part 6. Debugging in different environments

Chapter 37. Debugging DB2 programs

The topics below describe the steps for using Debug Tool to debug your DB2 programs.

- Chapter 11, “Preparing a DB2 program,” on page 49
- “Precompiling DB2 programs for debugging” on page 49
- “Compiling DB2 programs for debugging” on page 50
- “Linking DB2 programs for debugging” on page 50
- “Binding DB2 programs for debugging” on page 51
- “Debugging DB2 programs in batch mode”
- “Debugging DB2 programs in full-screen mode”
- Chapter 11, “Preparing a DB2 program,” on page 49

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

DB2 UDB for OS/390 Application Programming and SQL Guide

Debugging DB2 programs in batch mode

In order to debug your program with Debug Tool while in batch mode, follow these steps:

1. Make sure the Debug Tool modules are available, either by STEPLIB or through the LINKLIB.
2. Provide all the data set definitions in the form of DD statements (example: Log, Preference, list, and so on).
3. Specify your debug commands in the command input file.
4. Run your program through the TSO batch facility.

Debugging DB2 programs in full-screen mode

In full-screen mode, you can decide at debug time what debugging commands you want issued during the test.

Using Debug Tool Setup Utility (DTSU)

The Debug Tool Setup Utility is available through Debug Tool Utilities.

1. Start DTSU by using the TSO command or the ISPF panel option, if available. Contact your system administrator to determine if the ISPF panel option is available.
2. Create a setup file. Remember to select the **Initialize New setup file for DB2** field.
3. Fill in all the fields with the appropriate information. Remember to enter the proper commands in the **DSN command options** and the **RUN command options** fields.
4. Enter the RUN command to run the DB2 program.

Using TSO commands

1. Ensure that either you or your system programmer has allocated all the required data sets through a CLIST or REXX EXEC.
2. Issue the DSN command to start DB2.
3. Issue the RUN subcommand to execute your program. The TEST run-time option can be specified as a parameter on the RUN subcommand. An example for a COBOL program is:

```
RUN PROG(progname) PLAN(planname) LIB('user.library')
  PARMS('/TEST(*,*,*,*)')
```

Using TSO/Call Access Facility (CAF)

1. Link-edit the CAF language interface module DSNALI with your program.
2. Ensure that the data sets required by Debug Tool and your program have been allocated through a CLIST or REXX procedure.
3. Enter the TSO CALL command CALL '*user.library*(name of your program)', to start your program. Include the TEST run-time option as a parameter in this command.

In full-screen mode through a VTAM terminal

1. Specify the MFI%LU_name: parameter as part of the TEST option.
2. Follow the other requirements for debugging DB2 programs either under TSO or in batch mode.

After your program has been initiated, debug your program by issuing the required Debug Tool commands.

Note: If your source does not come up in Debug Tool when you launch it, check that the listing or source file name corresponds to the MVS library name, and that you have at least read access to that MVS library.

The program listing (for COBOL and PL/I) or program source (for C and C++) that Debug Tool displays and uses for the debug session is the output from the compile step and precompile step respectively, and thus includes all the DB2 expansion code produced by the DB2 precompiler. If you are compiling your program with a COBOL compiler option that support the SQL compiler option, the program listing does not include all the DB2 expansion code produced by the DB2 precompiler.

Refer to the following sections for more information related to the material discussed in this section.

Related references

DB2 UDB for OS/390 Administration Guide

Chapter 38. Debugging DB2 stored procedures

A DB2 stored procedure is a compiled high-level language (HLL) program that can run SQL statements. Debug Tool can debug in remote debug mode or full-screen mode through a VTAM terminal any stored procedure written in C, C++, COBOL, and PL/I. The program resides in an address space that is separate from the calling program. The stored procedure can be called by another application or a tool such as the IBM DB2 Stored Procedure Builder or IBM DB2 Development Center.

If you are going to debug a stored procedure while another user runs that stored procedure, do the following tasks:

- Compile the stored procedure with the TEST(ALL,SYM) compiler option. Do not compile it with the TEST(NONE,SYM) compiler option.
- You cannot use the Dynamic Debug facility. If you have the facility installed, use the SET DYNDEBUG OFF command as the first command at the start of your debug session.

The topics below describe the steps for using Debug Tool to debug your DB2 stored procedures.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 12, “Preparing a DB2 stored procedures program,” on page 53
“Starting Debug Tool from DB2 stored procedures: troubleshooting” on page 103

Related references

Chapter 12, “Preparing a DB2 stored procedures program,” on page 53
DB2 UDB for OS/390 Application Programming and SQL Guide

Resolving some common problems

While debugging a stored procedure, it is useful to add the DB2 return codes and message code variables (SQLCODE, SQLERRMC) to the Debug Tool Program Monitor. Table 6 are some common errors and suggestions for resolving them:

Table 6. Common problems while debugging stored procedures and resolutions to those problems

Error code	Error message	Resolution
SQLCODE = 471, SQLERRMC = 00E79001	Stored procedure was stopped.	Start the stored procedure using DB2 Start Procedure command.
SQLCODE = 471, SQLERRMC = 00E79002	Stored procedure could not be started because of a scheduling problem.	Try using the DB2 Start Procedure command. If this does not work, contact the DB2 Administrator to raise the dispatching priority of the procedure.

Table 6. Common problems while debugging stored procedures and resolutions to those problems (continued)

Error code	Error message	Resolution
SQLCODE = 471, SQLERRMC = 00E7900C	WLM application environment name is not defined or available.	Activate the WLM address space using the MVS WLM VARY command, for example: <pre>WLM VARY APPLENV=<i>applenv</i>,RESUME</pre> where <i>applenv</i> is the name of the WLM address space.
SQLCODE = 444, SQLERRMC (none)	Program not found.	Verify that the LOADLIB is in the STEPLIB for the WLM or DB2 address space JCL and has the appropriate RACF Read authorization for other applications to access it.
SQLCODE = 430, SQLERRMC (none)	Abnormal termination in stored procedure	This can occur for many reasons. If the stored procedure abends without calling Debug Tool, analyze the Procedure for any logic errors. If the Procedure runs successfully without Debug Tool, there may a problem with how the stored procedure was compiled and linked. Be sure that the Procedure data set has the proper RACF authorizations. There may be a problem with the address space. Verify that the WLM or DB2 Address Space is correct. If there are any modifications, be sure the region is recycled.

Chapter 39. Debugging IMS programs

You can use Debug Tool to debug IMS programs in the following ways:

- To debug your IMS Transaction Manager (TM) programs without Batch Terminal Simulator (BTS), use full-screen mode through a VTAM terminal or remote debug mode.
- To debug your IMS TM programs with BTS Full-Screen Image Support (FSS) to display your MFS screen formats on the TSO terminal, choose one of the following:
 - If you want all interaction to be on a single screen, use full-screen mode.
 - If you want BTS/FSS data displayed on your TSO terminal and your Debug Tool session to be displayed on another terminal, use full-screen mode through a VTAM terminal or remote debug mode.

FSS is the default option when BTS is started in the TSO foreground, and is available only when you are running BTS in the TSO foreground. FSS can only be turned off by specifying TSO=NO on the ./O command. When running in the TSO foreground, all call traces are displayed on your TSO terminal by default. This can be turned off by parameters on either the ./0 or ./T commands.

- To debug your batch IMS programs without BTS, use batch mode, full-screen mode through a VTAM terminal, or remote debug mode.
- To debug your batch IMS programs with BTS, choose one of the following:
 - If you want all interaction to be on a single screen, use full-screen mode.
 - If you want BTS data displayed on your TSO terminal and your Debug Tool session to be displayed on another terminal, use full-screen mode through a VTAM terminal or remote debug mode.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 14, “Preparing an IMS program,” on page 63

“Setting up the run-time options for your IMS Version 8 TM program by using Debug Tool Utilities” on page 64

“Linking IMS programs for debugging” on page 65

“Debugging IMS programs in interactive mode”

Related references

IMS/VS Batch Terminal Simulator Program Reference and Operations Manual

Debugging IMS programs in interactive mode

There are three ways to start Debug Tool in interactive mode:

- Specifying the MFI%LU_name: parameter of the TEST run-time option. This starts Debug Tool in full-screen mode with a VTAM terminal. The VTAM terminal controls the Debug Tool session.
- Specifying the VADTCPIP&tcPIP_workstation_id: or the TCP/IP&tcPIP_workstation_id: parameter of the TEST run-time option. This starts Debug Tool in remote debug mode with a remote debugger.
- Run BTS in the TSO foreground.

In interactive mode, Debug Tool commands can be entered as required.

If you want to debug an IMS batch program using the interactive mode of Debug Tool, do the following under BTS:

1. Define a *dummy* transaction code on the `./T` command to initiate your program
2. Include a *dummy* transaction in the BTS input stream
3. Start BTS in the TSO foreground

Note: If your source (C and C++) or listing (COBOL and PL/I) does not come up in Debug Tool when you launch it, check that the source or listing file name corresponds to the MVS library name, and that you have at least read access to that MVS library.

Currently, Debug Tool can only be used to debug one iteration of a transaction at a time. When the program terminates you must close down Debug Tool before you can view the output of the transaction.

Therefore, if you use an input data set, you can only specify data for one transaction in that data set. The data for the next transaction must be entered from your TSO terminal.

A new debug session will be started automatically for the next transaction. When using FSS, you must enter the `/*` command on your TSO terminal to terminate the BTS session.

Debugging IMS programs in batch mode

You can use Debug Tool to debug IMS programs in batch mode. The debug commands must be predefined and included in one of the Debug Tool command files, or in a command string. The command string can be specified as a parameter either in the TEST run-time option, or when CALL CEETEST or `__ctest` is used. Although batch mode consumes fewer resources, you must know beforehand exactly which debug commands you are going to issue. When you run BTS as a batch job, the batch mode of Debug Tool is the only mode available for use.

For example, you can allocate a data set, `userid.CODE.BTSINPUT` with individual members of test input data for IMS transactions under BTS.

Under IMS, you can start Debug Tool in the following ways:

- Use the compiler run-time option (`#pragma runopts` for C and C++)
- Include CSECT CEEUOPT when linking your program (for C and C++)
- Use the Language Environment callable service CEETEST (`__ctest()` for C and C++)

Chapter 40. Debugging CICS programs

Before you can debug your programs under CICS, verify that the following tasks have been completed:

- Verify that your Systems Programmer has made the appropriate changes to your CICS region to support Debug Tool (see the *Debug Tool for z/OS Customization Guide*).
- Depending on the compiler you are using, you need to ensure that your program is translated by the CICS translator either prior to or as part of the compilation. The following list describes the files you need to retain:
 - For C and C++: the program source file, after it has been through the CICS translator.
 - For COBOL: the program listing if you compiled with the NOSEP suboption of the TEST compiler option or the separate debug file if you compiled with the SEP suboption of the TEST compiler option. This is true for Enterprise COBOL compilers, regardless of whether you used the integrated CICS translator feature.
 - For PL/I (other than Enterprise PL/I): the program listing.
 - For Enterprise PL/I: the program source file generated by the CICS preprocessor, if you use the external CICS preprocessor. If you use integrated CICS preprocessor, you need to retain the program source file.
 - For assembler and OS/VS COBOL: the EQALANGX file.

To enhance the performance while using Debug Tool, use a large block size when you save these files. If you are using COBOL separate debug files, it is important that you allocate these files with the correct attributes to optimize the performance of Debug Tool. Use the following attributes for the PDS that contains the COBOL side file:

- RECFM=FB
- LRECL=1024
- BLKSIZE set so the system determines the optimal size

You must retain the file in a permanent data set for Debug Tool to read when you debug your program.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

- “Methods for starting Debug Tool under CICS” on page 96
- “Starting Debug Tool by using DTCN” on page 97
- “Link-editing EQADCCXT into your program” on page 55
- “Creating and storing a DTCN profile” on page 56
- “Starting Debug Tool by using CEEUOPT” on page 98
- “Starting Debug Tool by using compiler directives” on page 99
- “Starting Debug Tool under CICS by using CEDF” on page 99
- “Preventing Debug Tool from stopping at EXEC CICS RETURN” on page 284
- “Saving settings while debugging a pseudo-conversational program” on page 284

Related references

- “Debug modes under CICS” on page 284
- “Restrictions when debugging under CICS” on page 285

Debug modes under CICS

Debug Tool can run in several different modes, providing you with the flexibility to debug your applications in the way that suits you best. These modes include:

Single terminal mode

This is probably the mode you will use the most. A single 3270 session is used by both Debug Tool and the application, swapping displays on the terminal as required.

As you step through your application, the terminal shows Debug Tool screens, but when an EXEC CICS SEND command is issued, that screen will be displayed. Debug Tool holds that screen on the terminal for you to review; simply press Enter to return to a Debug Tool screen. When your application issues EXEC CICS RECEIVE, the application screen again appears, so you can fill in the screen details.

Dual terminal mode

This mode can be useful if you are debugging screen I/O applications. Debug Tool displays its screens on a separate 3270 session than the terminal displaying the application.

You step through the application using the Debug Tool terminal and, whenever the application issues an EXEC CICS SEND, the screen is sent to the application display terminal. Note that, if you do not code IMMEDIATE on the EXEC CICS SEND command, the buffer of data might be held within CICS Terminal Control until an optimum opportunity to send it is encountered—usually the next EXEC CICS SEND or EXEC CICS RECEIVE. When the application issues an EXEC CICS RECEIVE, the Debug Tool terminal will wait until you respond to the application terminal.

Interactive batch mode

Use this mode if you are debugging a transaction that does not have a terminal associated with it. The transaction continues to run without a CICS principal facility, but Debug Tool screens are displayed on a 3270 session that you name.

Noninteractive batch mode

In this mode, Debug Tool does not have a terminal associated to it at all. It receives its commands from a command file and writes its results to a log file. This mode is useful if you want Debug Tool to debug a program automatically.

Preventing Debug Tool from stopping at EXEC CICS RETURN

Debug Tool stops at EXEC CICS RETURN and displays the following message:
CEE0199W The termination of a thread was signaled due to a STOP statement.

To prevent Debug Tool from stopping at every EXEC CICS RETURN statement in your application and suppress this message, set the TEST level to ERROR by using the SET TEST ERROR command.

Saving settings while debugging a pseudo-conversational program

If you change the Debug Tool display settings (for example, color settings) while you debug a pseudo-conversational CICS program, Debug Tool might restore the default settings. To ensure that your changes remain in effect every time your program starts Debug Tool, store your display settings in the preferences file or the commands file.

Saving and restoring breakpoints (DTCN only)

When breakpoints are set in a CICS transaction, Debug Tool saves these breakpoint settings and restores them the next time this transaction is started. However, saving and restoring of breakpoints in assembler compilation units is not currently supported.

Restrictions when debugging under CICS

The following restrictions apply when debugging programs with the Debug Tool in a CICS environment.

- Debug Tool supports the use of CRTE terminals, if both the application and Debug Tool share the terminal as a principal facility in single terminal mode. CICS does not permit the use of a CRTE terminal by Debug Tool if the terminal is not the application task's principal facility (which is the case in Dual terminal mode).
- The `__ctest()` function with CICS does nothing.
- The CDT# transaction is a Debug Tool service transaction used during Dual terminal mode debugging and is not intended for activation by direct terminal input. If CDT# is started via terminal entry, it will return to the caller (no function is performed).
- Applications that issue EXEC CICS POST cannot be debugged in Dual Terminal mode.
- References to ddnames are not supported. All files, including the log file, USE files, and preferences file, must be referred to by their full data set names.
- The commands TS0, SET INTERCEPT, and SYSTEM cannot be used.
- CICS does not support an attention interrupt from the keyboard.
- The log file (INSPLOG) is not automatically started. You need to use the SET LOG ON command.
- Ensure that you allocate a log file big enough to hold all the log output from a debug session, because the log file is truncated after it becomes full. (A warning message is not issued before the log is truncated.)
- Save files (INSPSAFE) are not used under CICS.
- You can start Debug Tool when a non-Language Environment assembler or OS/VS COBOL program under CICS starts by defining a debug profile by using CADP or DTCN. But Debug Tool will only start on a CICS Link Level boundary, such as when the first program of the task starts or for the first program to run at a new Link Level. For profiles defined in CADP or DTCN which list a non-Language Environment assembler or OS/VS COBOL program name that is dynamically called using EXEC CICS LOAD/CALL, Debug Tool will not start. Non-Language Environment assembler or OS/VS COBOL programs that are called in this way are identified by Debug Tool in an already-running debugging session and can be stopped by using a command like AT APPEARANCE or AT ENTRY. However, they cannot be used to trigger a Debug Tool session initially.

Accessing CICS resources during a debugging session

You can gain access to CICS temporary storage and transient data queues during your debugging session by using the CALL %CEBR command. You can do all the functions you can currently do while in the CICS-supplied CEBR transaction. For access to general CICS resources (for example, information about the CICS system you are debugging on or opening and reading a VSAM file) you can use the CALL %CECI command. This command gives control to the CICS-supplied CECI

transaction. Press PF3 from inside CEBR or CECI to return to the debug session.
For more information on CEBR and CECI, see *CICS Supplied Transactions*.

Chapter 41. Debugging ISPF applications

You can debug ISPF applications in one of two ways:

- Using a separate terminal by specifying the LU name of a VTAM terminal as part of the TEST parameter. For example:
`TEST(,,MFI%TCP00001:)`
- Using the same emulator session. PA2 refreshes the ISPF application panel and removes residual Debug Tool output from the emulator session. However, if Debug Tool sends output to the emulator session between displays of the ISPF application panels, you need to press PA2 after each ISPF panel display.

The rest of this section assumes that you are debugging ISPF applications using the same emulator session.

When you debug ISPF applications or applications that use line mode input and output, issue the SET REFRESH ON command. This command is executed and is displayed in the log output area of the Command/Log window.

Because SET REFRESH ON modifies the Debug Tool environment, the REFRESH setting is saved in the preferences file (inspsafe), and it is preserved between Debug Tool invocations. You need to specify it only once; Debug Tool uses the same setting on subsequent invocations.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 29, “Customizing your full-screen session,” on page 193

Chapter 42. Debugging programs in a production environment

Programs in a production environment have any of the following characteristics:

- The programs are compiled without hooks.
- The programs are compiled with the optimization compiler option, usually the OPT compiler option.
- The programs are compiled with COBOL compilers that support the SEPARATE suboption of the TEST compiler option.

This section helps you determine how much of Debug Tool's testing functions you want to continue using after you complete major testing of your application and move into the final tuning phase. Included are discussions of program size and performance considerations; the consequences of removing hooks, the statement table, and the symbol table; and using Debug Tool on optimized programs.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Fine-tuning your programs with Debug Tool"

"Debugging without hooks, statement tables, and symbol tables" on page 290

"Debugging optimized COBOL programs" on page 291

Fine-tuning your programs with Debug Tool

After initial testing, you might want to consider the following options available to improve performance and reduce size:

- Removing the hooks, which can improve the performance of your program.
- Removing the statement and symbol tables, which can reduce the size of your program.

Removing hooks

One option for increasing the performance of your program is to compile with a minimum of hooks or with no hooks.

- For C programs, compiling with the option TEST(NOLINE,BLOCK,NOPATH) causes the compiler to insert a minimum number of hooks while still allowing you to perform tasks at block boundaries.
- For COBOL programs, compiling with the option TEST(NONE,SYM) creates programs that do not have hooks. Using the Dynamic Debug facility, Debug Tool inserts hooks while debugging the program, allowing you to perform almost any debugging task.

Independent studies show that performance degradation is negligible because of hook-overhead for PL/I programs. Also, in the event you need to request an attention interrupt, Debug Tool is not able to regain control without compiled-in hooks. In such a case you can request an interrupt three times. After the third time, Debug Tool is able to stop program execution and prompt you to enter QUIT or GO. If you enter QUIT, your Debug Tool session ends. If you enter GO, control is returned to your application.

Programs compiled with certain suboptions of the TEST compiler option have hooks inserted at compile time. However, if the Dynamic Debug facility is activated (which is the default) and the programs are compiled with certain compilers, the compiled-in hooks are replaced with run time hooks. This replacement is done to improve the performance of Debug Tool. Certain path hook functions are limited when you use the Dynamic Debug facility. To enable these functions, enter the SET DYNDEBUG OFF command, which deactivates the Dynamic Debug facility. See *Debug Tool for z/OS Reference and Messages* for a description of these commands.

It is a good idea to examine the benefits of maintaining hooks in light of the performance overhead for that particular program.

Removing statement and symbol tables

If you are concerned about the size of your program, you can remove the symbol table, the statement table, or both, after the initial testing period. For C and PL/I programs, compiling with the option TEST(NOSYM) inhibits the creation of symbol tables.

Before you remove them, however, you should consider their advantages. The statement table allows you to display the execution history with statement numbers rather than offsets, and error messages identify statement numbers that are in error. The symbol table enables you to refer to variables and program control constants by name. Therefore, you need to look at the trade-offs between the size of your program and the benefits of having symbol and statement tables.

For programs that are compiled with the following compilers and with the SEPARATE suboption of the TEST compiler option, the symbol tables are saved in a separate debug file. This arrangement lets you to retain the symbol table information and have a smaller program:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1, with APAR PQ40298

Debugging without hooks, statement tables, and symbol tables

Debug Tool can gain control at program initialization by using the PROMPT suboption of the TEST run-time option. Even when you have removed all hooks and the statement and symbol tables from a production program, Debug Tool receives control when a condition is raised in your program if you specify ALL or ERROR on the TEST run-time option, or when a `__ctest()`, `CEETEST`, or `PLITEST` is executed.

When Debug Tool receives control in this limited environment, it does not know what statement is in error (no statement table), nor can it locate variables (no symbol table). Thus, you must use addresses and interpret hexadecimal data values to examine variables. In this limited environment, you can:

- Determine the block that is in control:
`list (%LOAD, %CU, %BLOCK);`
or
`list (%LOAD, %PROGRAM, %BLOCK);`
- Determine the address of the error and of the compile unit:
`list (%ADDRESS, %EPA);` (where %EPA is allowed)

- Display areas of the program in hexadecimal format. Using your listing, you can find the address of a variable and display the contents of that variable. For example, you can display the contents at address 20058 in a C and C++ program by entering:

```
LIST STORAGE (0x20058);
```

To display the contents at address 20058 in a COBOL or PL/I program, you would enter:

```
LIST STORAGE (X'20058');
```

- Display registers:
`LIST REGISTERS;`
- Display program characteristics:
`DESCRIBE CU; (for C)`
`DESCRIBE PROGRAM; (for COBOL)`
- Display the dynamic block chain:
`LIST CALLS;`
- Request assistance from your operating system:
`SYSTEM ...;`
- Continue your program processing:
`GO;`
- End your program processing:
`QUIT;`

If your program does not contain a statement or symbol table, you can use session variables to make the task of examining values of variables easier.

Even in this limited environment, HLL library routines are still available.

Programs that are compiled with Enterprise COBOL for z/OS and OS/390 or COBOL for OS/390 & VM can have the best performance and smallest module size, while retaining full debugging capabilities, if they are compiled with the `TEST(NONE,SYM,SEPARATE)` compiler option. This option specifies that no hooks are inserted and symbol table information is saved in a separate debug file.

Debugging optimized COBOL programs

COBOL programs that are compiled with the following compilers are enhanced with features that make optimized programs easier to debug:

- Enterprise COBOL for z/OS and OS/390, Version 3 Release 2
- Enterprise COBOL for z/OS and OS/390, Version 3 Release 1, with APAR PQ63235
- COBOL for OS/390 & VM, Version 2, with APAR PQ63234

You must compile your COBOL programs with one of the following combinations of compiler options:

- `OPT(STD) TEST(NONE,SYM)`
- `OPT(STD) TEST(NONE,SYM,SEPARATE)`
- `OPT(FULL) TEST(NONE,SYM)`
- `OPT(FULL) TEST(NONE,SYM,SEPARATE)`

The following list describes the tasks you can do while debugging optimized COBOL programs:

- You can set breakpoints. If the optimizer moves or removes a statement, you can't set a breakpoint at that statement.
- You can display the value of a variable by using the LIST or LIST TITLED commands. Debug Tool displays the correct value of the variable.
- You can step through programs one statement at a time, or run your program until you encounter a breakpoint.
- You can use the SET AUTOMONITOR and PLAYBACK commands.
- You can change the value of a variable. Enter the SET WARNING OFF command before you begin modifying variables. You only need to enter the SET WARNING OFF command once during your debugging session. Whenever you enter a command that modifies the value of a variable, Debug Tool performs the command and displays a warning message. You must also apply APAR PQ71779 to Language Environment to take advantage of this feature.

The enhancements to the compilers help you create programs that can be debugged in the same way that you debug unoptimized programs. There are some exceptions:

- You cannot change the flow of your program.
- You cannot use the GOTO command.
- You cannot use the AT CALL *entry_name* command. Instead, use the AT CALL * command.
- If the optimizer discarded a variable, you can refer to the variable only by using the DESCRIBE ATTRIBUTES command. If you try to use any other command, Debug Tool displays a message indicating that the variable was discarded by the optimization techniques of the compiler.
- If you use the AT command, the following restrictions apply:
 - You cannot specify a line number where all the statements have been removed.
 - You cannot specify a range of line numbers where all the statements have been removed.
 - You cannot specify a range of line numbers where the beginning point or ending point specifies a line number where all the statements have been removed.

The Source window does display the variables and statements that the optimizer removed, but you cannot use any Debug Tool commands on those variables or statements. For example, you cannot list the value of a variable removed by the optimizer.

Chapter 43. Debugging UNIX System Services programs

You must debug your UNIX System Services programs in remote debug mode using a remote debugger, or in full-screen mode using a VTAM terminal. If your program spans more than one process, you must debug it in remote debug mode using a remote debugger. The remote debugger is available through several products, including C/C++ Productivity Tools for OS/390. If your program does not span more than one process, you can debug it in full-screen mode through a VTAM terminal.

If one or more of the programs you are debugging are in a shared library and you are using dynamic debugging, you need to assign the environment variable `_BPX_PTRACE_ATTACH` a value of YES. This enables Debug Tool to set hooks in the shared libraries. Programs that have a `.so` suffix are programs in a shared library. For more information on how to set environment variables, see your UNIX System Services documentation.

Debugging MVS POSIX programs

You can debug MVS POSIX programs, including the following types of programs:

- Programs that store source in HFS
- Programs that use POSIX multithreading
- Programs that use fork/exec
- Programs that use asynchronous signals that are handled by the Language Environment condition handler

To debug MVS POSIX programs in full screen mode or batch mode, the program must run under TSO or MVS batch. If you want to run your program under the UNIX SHELL, you must debug in full-screen mode through a VTAM terminal. To debug any MVS POSIX program that spans more than one process, you must debug the program in remote debug mode.

Chapter 44. Debugging non-Language Environment programs

There are several considerations that you must make when you debug programs that do not run under the Language Environment. Some of these are unique to programs that contain no Language Environment routines, others pertain only when the initial program does not execute under control of the Language Environment, and still others apply to all programs that have mixtures of non-Language Environment and Language Environment programs.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

Chapter 15, “Starting Debug Tool from the Debug Tool Utilities,” on page 69

Debugging exclusively non-Language Environment programs

When Language Environment is not active, you can debug only assembler, disassembly, or OS/VS COBOL programs. Debugging programs written in other languages requires the presence of an active Language Environment.

Debugging MVS batch or TSO non-Language Environment initial programs

If the initial program that is invoked does not run under Language Environment, and you want to begin debugging before Language Environment is initialized, you must use the EQANMDBG program to start both Debug Tool and your user program.

You do not have to use EQANMDBG to initiate a Debug Tool session if the initial user program runs under control of the Language Environment, even if other parts of the program do not run under the Language Environment.

Refer to the following sections for more information related to the material discussed in this section.

Related references

Chapter 18, “Starting Debug Tool for batch or TSO programs,” on page 89
z/OS Language Environment Debugging Guide

Debugging CICS non-Language Environment assembler or OS/VS COBOL initial programs

The non-Language Environment assembler or OS/VS COBOL program that you specify in a DTCN or CADP profile that starts a debugging session must be one of the following:

- The first program started for the CICS transaction.
- The first program that runs for an EXEC CICS LINK or XCTL statement.

Part 7. Debugging complex applications

Chapter 45. Debugging multilanguage applications

To support multiple high-level programming languages (HLL), Debug Tool adapts its commands to the HLLs, provides *interpretive subsets* of commands from the various HLLs, and maps common attributes of data types across the languages. It evaluates HLL expressions and handles constants and variables.

The topics below describe how Debug Tool makes it possible for you to debug programs consisting of different languages, structures, conventions, variables, and methods of evaluating expressions.

A general rule to remember is that Debug Tool tries to let the language itself guide how Debug Tool works with it.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Qualifying variables and changing the point of view” on page 301

“Debugging multilanguage applications” on page 305

“Handling conditions and exceptions in Debug Tool” on page 303

Related references

“Debug Tool evaluation of HLL expressions”

“Debug Tool interpretation of HLL variables and constants” on page 300

“Debug Tool commands that resemble HLL commands” on page 300

“Coexistence with other debuggers” on page 308

“Coexistence with unsupported HLL modules” on page 308

Debug Tool evaluation of HLL expressions

When you enter an expression, Debug Tool records the programming language in effect at that time. When the expression is run, Debug Tool passes it to the language run time in effect when you entered the expression. This run time might be different from the one in effect when the expression is run.

When you enter an expression that will not be run immediately, you should fully qualify all program variables. Qualifying the variables assures that proper context information (such as load module and block) is passed to the language run time when the expression is run. Otherwise, the context might not be the one you intended when you set the breakpoint, and the language run time might not evaluate the expression.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Debug Tool evaluation of C and C++ expressions” on page 245

“Debug Tool evaluation of COBOL expressions” on page 215

“Debug Tool evaluation of PL/I expressions” on page 232

Debug Tool interpretation of HLL variables and constants

Debug Tool supports the use of HLL variables and constants, both as a part of evaluating portions of your test program and in declaring and using session variables.

Three general types of variables supported by Debug Tool are:

- Program variables defined by the HLL compiler's symbol table
- Debug Tool variables denoted by the percent (%) sign
- Session variables declared for a given Debug Tool session and existing only for the session

HLL variables

Some variable references require language-specific evaluation, such as pointer referencing or subscript evaluation. Once again, the Debug Tool interprets each case in the manner of the HLL in question. Below is a list of some of the areas where Debug Tool accepts a different form of reference depending on the current programming language:

- Structure qualification
C and C++ and PL/I: dot (.) qualification, high-level to low-level
COBOL: IN or OF keyword, low-level to high-level
- Subscripting
C and C++: name [subscript1][subscript2]...
COBOL and PL/I: name(subscript1,subscript2,...)
- Reference modification
COBOL name(left-most-character-position: length)

HLL constants

You can use both string constants and numeric constants. Debug Tool accepts both types of constants in C and C++, COBOL, and PL/I.

Debug Tool commands that resemble HLL commands

To allow you to use familiar commands while in a debug session, Debug Tool provides an *interpretive subset* of commands for each language. This consists of commands that have the same syntax, whether used with Debug Tool or when writing application programs. You use these commands in Debug Tool as though you were coding in the original language.

Use the SET PROGRAMMING LANGUAGE command to set the current programming language to the desired language. The current programming language determines how commands are parsed. If you SET PROGRAMMING LANGUAGE to AUTOMATIC, every time the current qualification changes to a module in a different language, the current programming language is automatically updated.

The following types of Debug Tool commands have the same syntax (or a subset of it) as the corresponding statements (if defined) in each supported programming language:

Assignment

These commands allow you to assign a value to a variable or reference.

Conditional

These commands evaluate an expression and control the flow of execution of Debug Tool commands according to the resulting value.

Declarations

These commands allow you to declare session variables.

Looping

These commands allow you to program an iterative or logical loop as a Debug Tool command.

Multiway

These commands allow you to program multiway logic in the Debug Tool command language.

In addition, Debug Tool supports special kinds of commands for some languages.

Related references

“Debug Tool commands that resemble C and C++ commands” on page 237

“Debug Tool commands that resemble COBOL statements” on page 209

Qualifying variables and changing the point of view

Each HLL defines a concept of name scoping to allow you, within a single compile unit, to know what data is referenced when a name is used (for example, if you use the same variable name in two different procedures). Similarly, Debug Tool defines the concepts of qualifiers and point of view for the run-time environment to allow you to reference all variables in a program, no matter how many subroutines it contains. The assignment `x = 5` does not appear difficult for Debug Tool to process. However, if you declare `x` in more than one subroutine, the situation is no longer obvious. If `x` is not in the currently executing compile unit, you need a way to tell Debug Tool how to determine the proper `x`.

You also need a way to change the Debug Tool’s point of view to allow it to reference variables it cannot currently see (that is, variables that are not within the scope of the currently executing block or compile unit, depending upon the HLL’s concept of name scoping).

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Qualifying variables”

“Changing the point of view” on page 303

Qualifying variables

Qualification is a method you can use to specify to what procedure or load module a particular variable belongs. You do this by prefacing the variable with the block, compile unit, and load module (or as many of these labels as are necessary), separating each label with a colon (or double colon following the load module specification) and a greater-than sign (`:`), as follows:

```
load_name:::cu_name:>block_name:>object
```

This procedure, known as *explicit qualification*, lets Debug Tool know precisely where the variable is.

If required, *load_name* is the load module name. It is required only when the program consists of multiple load modules and when you want to change the qualification to other than the current load module. *load_name* can be the Debug Tool variable %LOAD.

If required, *cu_name* is the compile unit name. The *cu_name* is required only when you want to change the qualification to other than the currently qualified compile unit. *cu_name* can be the Debug Tool variable %CU.

If required, *block_name* is the program block name. The *block_name* is required only when you want to change the qualification to other than the currently qualified block. *block_name* can be the Debug Tool variable %BLOCK.

For PL/I only:

In PL/I, the primary entry name of the external procedure is the same as the compile unit name. When qualifying to the external procedure, the procedure name of the top procedure in a compile unit fully qualifies the block. Specifying both the compile unit and block name results in an error. For example:

```
LM::>PROC1:>variable
```

is valid.

```
LM::>PROC1:>PROC1:>variable
```

is not valid.

For C++ only:

You must specify the full function qualification including formal parameters where they exist. For example:

1. For function (or block) ICCD2263() declared as void ICCD2263(void) within CU "USERID.SOURCE.LISTING(ICCD226)" the correct block specification for C++ would include the parenthesis () as follows:
qualify block %load::>"USERID.SOURCE.LISTING(ICCD226)":>ICCD2263()
2. For CU ICCD0320() declared as int ICCD0320(signed long int SVAR1, signed long int SVAR2) the correct qualification for AT ENTRY is:

```
AT ENTRY "USERID.SOURCE.LISTING(ICCD0320)":>ICCD0320(long,long)
```

Use the Debug Tool command DESCRIBE CUS to give you the correct BLOCK or CU qualification needed.

Use the LIST NAMES command to show all polymorphic functions of a given name. For the example above, LIST NAMES "ICCD0320*" would list all polymorphic functions called ICCD0320.

You do not have to preface variables in the currently executing compile unit. These are already known to Debug Tool; in other words, they are *implicitly* qualified.

In order for attempts at qualifying a variable to work, each block must have a name. Blocks that have not received a name are named by Debug Tool, using the form: %BLOCK nnn , where nnn is a number that relates to the position of the block in the program. To find out the Debug Tool's name for the current block, use the DESCRIBE PROGRAMS command.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Qualifying variables and changing the point of view in C and C++” on page 252

“Qualifying variables and changing the point of view in COBOL” on page 217

Changing the point of view

The point of view is usually the currently executing block. You can get to inaccessible data by changing the point of view using the SET QUALIFY command with the following operand.

`load_name::>cu_name:>block_name`

Each time you update any of the three Debug Tool variables %CU, %PROGRAM, or %BLOCK, all four variables (%CU, %PROGRAM, %LOAD, and %BLOCK) are automatically updated to reflect the new point of view. If you change %LOAD using SET QUALIFY LOAD, only %LOAD is updated to the new point of view. The other three Debug Tool variables remain unchanged. For example, suppose your program is currently suspended at loadx::>cux:>blockx. Also, the load module loadz, containing the compile unit cuz and the block blockz, is known to Debug Tool. The settings currently in effect are:

```
%LOAD = loadx
%CU = cux
%PROGRAM = cux
%BLOCK = blockx
```

If you enter any of the following commands:

```
SET QUALIFY BLOCK blockz;
```

```
SET QUALIFY BLOCK cuz:>blockz;
```

```
SET QUALIFY BLOCK loadz::>cuz:>blockz;
```

the following settings are in effect:

```
%LOAD = loadz
%CU = cuz
%PROGRAM = cuz
%BLOCK = blockz
```

If you are debugging a program that has multiple enclaves, SET QUALIFY can be used to identify references and statement numbers in any enclave by resetting the point of view to a new block, compile unit, or load module.

Related tasks

Chapter 47, “Debugging across multiple processes and enclaves,” on page 311

“Changing the point of view in C and C++” on page 253

“Changing the point of view in COBOL” on page 219

Handling conditions and exceptions in Debug Tool

To suspend program execution just before your application would terminate abnormally, start your application with the following runtime options:

```
TRAP(ON)
TEST(ALL,*,NOPROMPT,*)
```

When a condition is signaled in your application, Debug Tool prompts you and you can then *dynamically* code around the problem. For example, you can initialize a pointer, allocate memory, or change the course of the program with the GOTO command. You can also indicate to Language Environment’s condition handler, that you have handled the condition by issuing a GO BYPASS command. Be aware

that some of the code that follows the instruction that raised the condition might rely on data that was not properly stored or handled.

When debugging with Debug Tool, you can (depending on your host system) either instruct the debugger to handle program exceptions and conditions, or pass them on to your own exception handler. Programs also have access to Language Environment services to deal with program exceptions and conditions.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Handling conditions in Debug Tool”

“Handling exceptions within expressions (C and C++ and PL/I only)” on page 305

Handling conditions in Debug Tool

You can use either or both of the two methods during a debugging session to ensure that Debug Tool gains control at the occurrence of HLL conditions.

If you specify TEST(ALL) as a run-time option when you begin your debug session, Debug Tool gains control at the occurrence of most conditions.

Note: Debug Tool recognizes all Language Environment conditions that are detected by the Language Environment error handling facility.

You can also direct Debug Tool to respond to the occurrence of conditions by using the AT OCCURRENCE command to define breakpoints. These breakpoints halt processing of your program when a condition is raised, after which Debug Tool is given control. It then processes the commands you specified when you defined the breakpoints.

There are several ways a condition can occur, and several ways it can be handled.

When a condition can occur

A condition can occur during your Debug Tool session when:

- A C++ application throws an exception.
- A C and C++ application program executes a raise statement.
- A PL/I application program executes a SIGNAL statement.
- The Debug Tool command TRIGGER is executed.
- Program execution causes a condition to exist. In this case, conditions are not raised at consistency points (the operations causing them can consist of several machine instructions, and consistency points usually occur at the beginnings and ends of statements).
- The setting of WARNING is OFF (for C and C++ and PL/I).

When a condition occurs

When an HLL condition occurs and you have defined a breakpoint with associated actions, those actions are first performed. What happens next depends on how the actions end.

- Your program’s execution can be terminated with a QUIT command. If you are debugging a CICS non-Language Environment assembler or OS/VS COBOL programs, QUIT ends Debug Tool and the task ends with an ABEND 4038.
- Control of your program’s execution can be returned to the HLL exception handler, using the GO command, so that processing proceeds as if Debug Tool

had never been invoked (even if you have perhaps used it to change some variable values, or taken some other action).

- Control of your program's execution can be returned to the program itself, using the G0 BYPASS command, bypassing any further processing of this exception either by the user program or the environment.
- PL/I allows G0 T0 out of block;, so execution control can be passed to some other point in the program.
- If no circumstances exist explicitly directing the assignment of control, your primary commands file or terminal is queried for another command.

If, after the execution of any defined breakpoint, control returns to your program with a G0, the condition is raised again in the program (if possible and still applicable). If you use a G0T0 to bypass the failing statement, you also bypass your program's error handling facilities.

Refer to the following sections for more information related to the material discussed in this section.

Related references

"Language Environment conditions and their C and C++ equivalents" on page 244

"PL/I conditions and condition handling" on page 229

z/OS Language Environment Programming Guide

Enterprise COBOL for z/OS and OS/390 Language Reference

Handling exceptions within expressions (C and C++ and PL/I only)

When an exception such as division by zero is detected in a Debug Tool expression, you can use the Debug Tool command SET WARNING to control Debug Tool and program response. During an interactive Debug Tool session, such exceptions are sometimes due to typing errors and so are probably not intended to be passed to the program. If you do not want errors in Debug Tool expressions to be passed to your program, use SET WARNING ON. Expressions containing such errors are terminated, and a warning message is displayed.

However, you might want to pass an exception to your program, perhaps to test an error recovery procedure. In this case, use SET WARNING OFF.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

"Using SET WARNING PL/I command with built-in functions" on page 234

Debugging multilanguage applications

Language Environment simplifies the debugging of multilanguage applications by providing a single run-time environment and interlanguage communication (ILC).

When the need to debug a multilanguage application arises, you can find yourself facing one of the following scenarios:

- You need to debug an application written in more than one language, where each language is supported by Language Environment and can be debugged by Debug Tool.

- You need to debug an application written in more than one language, where not all of the languages are supported by Language Environment, nor can they be debugged by Debug Tool.

When writing a multilanguage application, a number of special considerations arise because you must work outside the scope of any single language. The Language Environment initialization process establishes an environment tailored to the set of HLLs constituting the main load module of your application program. This removes the need to make explicit calls to manipulate the environment. Also, termination of the Language Environment environment is accomplished in an orderly fashion, regardless of the mixture of HLLs present in the application.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Debugging an application fully supported by Language Environment”

“Using session variables across different languages”

Debugging an application fully supported by Language Environment

If you are debugging a program written in a combination of languages supported by Language Environment and compiled by supported compilers, very little is required in the way of special actions. Debug Tool normally recognizes a change in programming languages and automatically switches to the correct language when a breakpoint is reached. If desired, you can use the SET PROGRAMMING LANGUAGE command to stay in the language you specify; however, you can only access variables defined in the currently set programming language.

When defining session variables you want to access from compile units of different languages, you must define them with compatible attributes.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Using session variables across different languages”

Related references

z/OS Language Environment Programming Guide

Using session variables across different languages

While working in one language, you can declare session variables that you can continue to use after calling in a load module of a different language. The table below shows how the attributes of session variables are mapped across programming languages. Session variables with attributes not shown in the table cannot be accessed from other programming languages. (Some attributes supported for C and C++ or PL/I session variables cannot be mapped to other languages; session variables defined with these attributes cannot be accessed outside the defining language. However, all of the supported attributes for COBOL session variables can be mapped to equivalent supported attributes in C and C++ and PL/I, so any session variable that you declare with COBOL can be accessed from C and C++ and PL/I.)

Machine attributes	PL/I attributes	C and C++ attributes	COBOL attributes	Assembler and disassembly attributes
byte	CHAR(1)	unsigned char	PICTURE X	DS X or DS C
byte string	CHAR(j)	unsigned char[j]	PICTURE X(j)	DS XLj or DS CLj
halfword	FIXED BIN(15,0)	signed short int	PICTURE S9(j≤4) USAGE BINARY	DS H
fullword	FIXED BIN(31,0)	signed long int	PICTURE S9(4<j≤9) USAGE BINARY	DS F
floating point	FLOAT BIN(21) or FLOAT DEC(6)	float	USAGE COMP-1	DS E
long floating point	FLOAT BIN(53) or FLOAT DEC(16)	double	USAGE COMP-2	DS D
extended floating point	FLOAT BIN(109) or FLOAT DEC(33)	long double	n/a	DS L
fullword pointer	POINTER	*	USAGE POINTER	DS A

Note: When registering session variables in PL/I, the DECIMAL type is always the default. For example, if C declares a float, PL/I registers the variable as a FLOAT DEC(6) rather than a FLOAT BIN(21).

When declaring session variables, remember that C and C++ variable names are case-sensitive. When the current programming language is C and C++, only session variables that are declared with uppercase names can be shared with COBOL or PL/I. When the current programming language is COBOL or PL/I, session variable names in mixed or lowercase are mapped to uppercase. These COBOL or PL/I session variables can be declared or referenced using any mixture of lowercase and uppercase characters and it makes no difference. However, if the session variable is shared with C and C++, within C and C++, it can only be referred to with all uppercase characters (since a variable name composed of the same characters, but with one or more characters in lowercase, is a different variable name in C and C++).

Session variables with incompatible attributes cannot be shared between other programming languages, but they do cause session variables with the same names to be deleted. For example, COBOL has no equivalent to PL/I's FLOAT DEC(33) or C's long double. With the current programming language COBOL, if a session variable X is declared PICTURE S9(4), it will exist when the current programming language setting is PL/I with the attributes FIXED BIN(15,0) and when the current programming language setting is C with the attributes signed short int. If the current programming language setting is changed to PL/I and a session variable X is declared FLOAT DEC(33), the X declared by COBOL will no longer exist. The variable X declared by PL/I will exist when the current programming language setting is C with the attributes long double.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Debug Tool interpretation of HLL variables and constants” on page 300

Coexistence with other debuggers

Debug Tool can coexist with low-level debugging facilities, such as TSO TEST. However, coexistence with other HLL debuggers cannot be guaranteed.

C, C++, COBOL, and PL/I are dependent upon Language Environment to provide debugging information.

Another debugger might provide limited services for an HLL not yet supported by Debug Tool, but conditions such as attention interrupts and exceptions cause Language Environment to pass control to an installed Language Environment debugger.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Coexistence with unsupported HLL modules”

Coexistence with unsupported HLL modules

Compile units or program units written in unsupported high- or low-level languages, or in older releases of HLLs, are tolerated. See *Using CODE/370 with VS COBOL II and OS PL/I* for information about two unsupported HLLs that can be used with Debug Tool.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Coexistence with other debuggers”

Chapter 46. Debugging multithreading programs

You can run your multithreading programs with Debug Tool. When more than one task is involved in your program, Debug Tool might be started by any or all of them. Because conflicting use of the terminal or log file, for example, could occur if Debug Tool is operating on multiple tasks, its use is single-threaded. So, if your program runs as two tasks (task A and task B) and task A calls Debug Tool, Debug Tool accepts the request and begins operating on behalf of task A. If, during that period, task B calls Debug Tool, the request from task B is held until the request from task A is complete (for example, you issued a STEP or GO command). Debug Tool is then released and can accept any pending invocation.

Restrictions when debugging multithreading applications

- Debugging applications that create another process is constrained because both processes compete for the use of the terminal.
- Only the variables and symbol information for compile units in the task that is being debugged are accessible.
- The LIST CALL command provides a traceback of the compile units only in the current task.

Refer to the following sections for more information related to the material discussed in this section.

Related references

z/OS Language Environment Programming Guide

Chapter 47. Debugging across multiple processes and enclaves

There is a single Debug Tool session across all enclaves in a process. Breakpoints set in one process are restored when the new process begins in the new session.

In full-screen mode or batch mode, you can debug a non-POSIX program that spans more than one process, but Debug Tool can be active in only one process. In remote debug mode, you can debug a POSIX program that spans more than one process. The remote debugger can display each process.

When you are recording the statements that you run, data collection persists across multiple enclaves until you stop recording. When you replay your statements, the data is replayed across the enclave boundaries in the same order as they were recorded.

A commands file continues to execute its series of commands regardless of what level of enclave is entered.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Starting Debug Tool within an enclave”

“Viewing Debug Tool windows across multiple enclaves” on page 312

“Ending a Debug Tool session within multiple enclaves” on page 312

“Using Debug Tool commands within multiple enclaves” on page 312

Starting Debug Tool within an enclave

After an enclave in a process activates Debug Tool, it remains active throughout subsequent enclaves in the process, regardless of whether the run-time options for the enclave specify TEST or NOTEST. Debug Tool retains the settings specified from the TEST run-time option for the enclave that activated it, until you modify them with SET TEST. If your Debug Tool session includes more than one process, the settings for TEST are reset according to those specified on the TEST run-time option of the first enclave that activates Debug Tool in each new process.

If Debug Tool is first activated in a nested enclave of a process, and you step or go back to the parent enclave, you can debug the parent enclave. However, if the parent enclave contains COBOL but the nested enclave does not, Debug Tool is not active for the parent enclave, even upon return from the child enclave.

Upon activation of Debug Tool, the initial commands string, primary commands file, and the preferences file are run. They run only once, and affect the entire Debug Tool session. A new primary commands file cannot be started for a new enclave.

Viewing Debug Tool windows across multiple enclaves

When an enclave starts another enclave, the Source or Listing windows and their related windows (Compact Source, Local Breakpoint, and Local Monitor windows) of the first enclave are hidden. You cannot open a Source or Listing window for a compile unit unless that compile unit is in the current enclave.

Ending a Debug Tool session within multiple enclaves

If you specify the NOPROMPT suboption of the TEST run time option for the next process on the host, Debug Tool restores the saved breakpoints after it gains control of that next process. However, Debug Tool might gain control of the process after many statements have been run. Therefore, Debug Tool might not run some or all of the following breakpoints:

- STATEMENT/LINE
- ENTRY
- EXIT
- LABEL

If you have not used these breakpoint types, you can specify NOPROMPT.

In a single enclave, QUIT closes Debug Tool. For CICS non-Language Environment programs (assembler or OS/VS Cobol), QUIT closes Debug Tool and the task ends with an ABEND 4038, regardless of the link level.

In a nested enclave, however, QUIT causes Debug Tool to signal a severity 3 condition that corresponds to Language Environment message CEE2529S. The system is trying to cleanly terminate all enclaves in the process.

Normally, the condition causes the current enclave to terminate. Then, the same condition will be raised in the parent enclave, which will also terminate. This sequence continues until all enclaves in the process have been terminated. As a result, you will see a CEE2529S message for each enclave that is terminated.

For CICS and MVS only: Depending on Language Environment run-time settings, the application might be terminated with an ABEND 4038. This termination is normal and should be expected.

Using Debug Tool commands within multiple enclaves

Some Debug Tool commands and variables have a specific scope for enclaves and processes. The table below summarizes the behavior of specific Debug Tool commands and variables when you are debugging an application that consists of multiple enclaves.

Debug Tool command	Affects current enclave only	Affects entire Debug Tool session	Comments
%CAAADDRESS	X		
AT GLOBAL		X	
AT TERMINATION		X	
CLEAR AT	X	X	In addition to clearing breakpoints set in the current enclave, CLEAR AT can clear global breakpoints.

Debug Tool command	Affects current enclave only	Affects entire Debug Tool session	Comments
CLEAR DECLARE		X	
CLEAR VARIABLES		X	
Declarations		X	Session variables are cleared at the termination of the process in which they were declared.
DISABLE	X	X	In addition to disabling breakpoints set in the current enclave, DISABLE can disable global breakpoints.
ENABLE	X	X	In addition to enabling breakpoints set in the current enclave, ENABLE can enable global breakpoints.
LIST AT	X	X	In addition to listing breakpoints set in the current enclave, LIST AT can list global breakpoints.
LIST CALLS	X		Applies to all systems except MVS batch and MVS with TSO. Under MVS batch and MVS with TSO, LIST CALLS lists the call chain for the current active thread in the current active enclave. For programs containing interlanguage communication (ILC), routines from previous enclaves are only listed if they are coded in a language that is active in the current enclave. Note: Only compile units in the current thread will be listed for PL/I multitasking applications.
LIST EXPRESSION	X		You can only list variables in the currently active thread.
LIST LAST		X	
LIST NAMES CUS		X	Applies to compile unit names. In the Debug Frame window, compile units in parent enclaves are marked as deactivated.
LIST NAMES TEST		X	Applies to Debug Tool session variable names.
MONITOR GLOBAL		X	Applies to Global monitors.
PLAYBACK ENABLE		X	The PLAYBACK command that informs Debug Tool to begin the recording session.
PLAYBACK DISABLE		X	The PLAYBACK command that informs Debug Tool to stop the recording session.
PLAYBACK START		X	The PLAYBACK command that suspends execution of the program and indicates to Debug Tool to enter replay mode.
PLAYBACK STOP		X	The PLAYBACK command that terminates replay mode and resumes normal execution of Debug Tool.
PLAYBACK BACKWARD		X	The PLAYBACK command that indicates to Debug Tool to perform STEP and RUNTO commands backward, starting from the current point and going to previous points.

Debug Tool command	Affects current enclave only	Affects entire Debug Tool session	Comments
PLAYBACK FORWARD		X	The PLAYBACK command that indicates to Debug Tool to perform STEP and RUNTO commands forward, starting from the current point and going to the next point.
PROCEDURE		X	
SET AUTOMONITOR ¹	X		Controls the monitoring of data items at the currently executing statement.
SET COUNTRY ¹	X		This setting affects both your application and Debug Tool. At the beginning of an enclave, the settings are those provided by Language Environment or your operating system. For nested enclaves, the parent's settings are restored upon return from a child enclave.
SET EQUATE ¹		X	
SET INTERCEPT ¹		X	For C, intercepted streams or files cannot be part of any C I/O redirection during the execution of a nested enclave. For example, if stdout is intercepted in program A, program A cannot then redirect stdout to stderr when it does a system() call to program B. Also, not supported for PL/I.
SET NATIONAL LANGUAGE ¹	X		This setting affects both your application and Debug Tool. At the beginning of an enclave, the settings are those provided by Language Environment or your operating system. For nested enclaves, the parent's settings are restored upon return from a child enclave.
SET PROGRAMMING LANGUAGE ¹	X		Applies only to programming languages in which compile units known in the current enclave are written (a language is "known" the first time it is entered in the application flow).
SET QUALIFY ¹	X		Can only be issued for load modules, compile units, and blocks that are known in the current enclave.
SET TEST ¹		X	
TRIGGER condition ²	X		Applies to triggered conditions. ² Conditions can be either an Language Environment symbolic feedback code, or a language-oriented keyword or code, depending on the current programming language setting.
TRIGGER AT	X	X	In addition to triggering breakpoints set in the current enclave, TRIGGER AT can trigger global breakpoints.

Notes:

1. SET commands other than those listed in this table affect the entire Debug Tool session.

2. If no active condition handler exists for the specified condition, the default condition handler can cause the program to end prematurely.

Chapter 48. Debugging a multiple-enclave interlanguage communication (ILC) application

When you debug a multiple-enclave ILC application with Debug Tool, use the SET PROGRAMMING LANGUAGE to change the current programming language setting. The programming language setting is limited to the languages currently known to Debug Tool (that is, languages contained in the current load module).

Command lists on monitors and breakpoints have an implied programming language setting, which is the language that was in effect when the monitor or breakpoint was established. Therefore, if you change the language setting, errors might result when the monitor is refreshed or the breakpoint is triggered.

Part 8. Appendixes

Appendix A. Data sets used by Debug Tool

Debug Tool uses the following data sets:

C and C++ source

This data set is used as input to the compiler, and must be kept in a permanent PDS member, sequential file, or HFS file. The data set must be a single file, not a concatenation of files. Debug Tool uses the data set to show you the program as it is executing.

The C and C++ compilers store the name of the source data set inside the load module. Debug Tool uses this data set name to access the source.

This data set might not be the original source; for example, the program might have been preprocessed by the CICS translator. If you use a preprocessor, you must keep the data set input to the compiler in a permanent data set for later use with Debug Tool.

As this data set might be read many times by Debug Tool, we recommend that you do one of the following:

- Define it with the largest block size that your DASD can hold.
- Instruct the system to compute the optimum block size, if your system has that capability.

COBOL listing

This data set is produced by the compiler and must be kept in a permanent PDS member, sequential file, or HFS file. Debug Tool uses it to show you the program as it is executing.

The COBOL compiler stores the name of the listing data set inside the load module. Debug Tool uses this data set name to access the listing.

Debug Tool does not use the output that is created by the COBOL LIST compiler option.

COBOL programs that have been compiled with the SEPARATE suboption do not need to save the listing file. Instead, you must save the separate debug file SYSDEBUG.

The VS COBOL II compilers do not store the name of the listing data set. Debug Tool creates a name in the form `userid.cuname.LIST` and uses that name to find the listing.

Because this data set might be read many times by Debug Tool, we recommend that you do one of the following:

- Define it with the largest block size that your DASD can hold.
- Instruct the system to compute the optimum blocksize, if your system has that capability.

EQALANGX file

Debug Tool uses this data set to obtain debug information about assembler and OS/VS COBOL source files. It can be a permanent PDS member or sequential file. You must create it before you start Debug Tool. You can create it by using the EQALANGX program. Use the SYSADATA output from the High Level assembler as input to the EQALANGX program.

PL/I source (Enterprise PL/I only)

This data set is used as input to the compiler, and must be kept in a

permanent PDS member, sequential file, or HFS file. Debug Tool uses it to show you the program as it is executing.

The Enterprise PL/I compiler stores the name of the source data set inside the load module. Debug Tool uses this data set name to access the source.

This data set might not be the original source; for example, the program might have been preprocessed by the CICS translator. If you use a preprocessor, you must keep the data set input to the compiler in a permanent data set, for later use with Debug Tool.

Because this data set might be read many times by Debug Tool, we recommend that you do one of the following:

- Define it with the largest block size that your DASD can hold.
- Instruct the system to compute the optimum block size, if your system has that capability.

PL/I listing (all other versions of PL/I compiler)

This data set is produced by the compiler and must be kept in a permanent file. Debug Tool uses it to show you the program as it is executing.

The PL/I compiler does not store the name of the listing data set. Debug Tool looks for the listing in a data set with the name in the form of `userid.cuname.LIST`.

Debug Tool does not use the output that is created by the PL/I compiler LIST option; performance improves if you specify NOLIST.

Because this data set might be read many times by Debug Tool, we recommend that you do one of the following:

- Define it with the largest block size that your DASD can hold.
- Instruct the system to compute the optimum block size, if your system has that capability.

Separate debug file

This data set is produced by the compiler when you compile your program with the SEPARATE compiler suboption of the TEST compiler option. It should be kept in a permanent PDS member, sequential file, or HFS file. The SEPARATE compiler suboption is available on the following compilers:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298

The COBOL compiler stores the data set name of the separate debug file inside the load module. Debug Tool uses this data set name to access the listing and other debug data, such as the symbol table. The DD name used by the COBOL compiler for the separate debug file is `SYSDEBUG`.

Because this data set might be read many times by Debug Tool, we recommend that you do one of the following:

- Define it with the largest block size that your DASD can hold.
- Instruct the system to compute the optimum block size, if your system has that capability.

Preferences file

This data set contains Debug Tool commands that customize your session. You can use it, for example, to change the default screen colors set by Debug Tool. It should be kept in a permanent PDS member or a sequential file.

The default DD name for the Debug Tool preferences file is INSPREF.

Preferences files are not used in remote debug mode.

Global preferences file

This data set is similar to the preferences file, but it is specified through the EQAOPTS options load module. See the *Debug Tool for z/OS Customization Guide* for more information on the EQAOPTS options load module. If a global preferences file exists, the commands specified in it are run before commands found in the preferences file.

Global Preferences file is not used in remote debug mode.

Commands file

This data set contains Debug Tool commands that control the debug session. You can use it, for example, to set breakpoints or set up monitors for common variables. It should be kept in a permanent PDS member or a sequential file.

If a preferences file is available, the commands in the commands file are run *after* the commands specified in the preferences file.

Commands files are not used in remote debug mode.

Log file

Debug Tool uses this file to record the progress of the debugging session. The results of the execution of commands are saved as comments. This allows you to use the log file as a commands file in subsequent debugging sessions. It should be kept in a permanent PDS member or a sequential file. As this data set is written to by Debug Tool, we recommend you use a sequential file to relieve any contentions for this file.

The DD name for the Debug Tool log file is INSPLOG.

Log files are not used in remote debug mode.

Save file

Debug Tool uses this file to store preference settings such as screen colors and panel layouts at the end of each session. These settings are then restored at the start of subsequent sessions. It should be kept in a permanent PDS member or a sequential file. As this data set is written to by Debug Tool, we recommend you use a sequential file to relieve any contentions for this file. The file must have a record format of Fixed and a record length of 80.

The DD name for the Debug Tool save file is INSPSAFE.

Save files are not used for remote debug sessions.

Save files are not used under CICS.

Refer to the following sections for more information related to the material discussed in this section.

Related references

“Format for a COBOL source listing and debug file” on page 209

Appendix B. How does Debug Tool locate debug information and source or listing files?

Debug Tool obtains information (called debug information) it needs about a compilation unit (CU) by searching through the following sources:

1. In most cases, the debug information is found in the load module. In conjunction with this information, Debug Tool uses the information in the source or listing file to display source code on the screen.
2. For COBOL CUs compiled with the SEPARATE suboption of the TEST compiler option, Debug Tool uses the information stored in a separate file (called a side file) that contains both the debug information and the information needed to display source code on the screen.
3. For assembler CUs, Debug Tool uses the information stored in a separate file (called an EQALANGX file) that contains both the debug information and the information needed to display source code on the screen.

In all of these cases, there is a default data set name associated with each CU. This name is either the name of the data set where the compiler processed the source, listing, or side file or a name constructed from the CU name. The way this default name is generated differs depending on the source language and compiler used. See Appendix A, "Data sets used by Debug Tool," on page 321 for a description of this default name and how it is generated for each language and compiler.

The source or listing data, side file data, or EQALANGX data is obtained from one of the following sources:

- the default data set name
- the SET SOURCE command
- the SET DEFAULT LISTINGS command
- the EQADEBUG DD statement

The order in which these are located is different for each type of file. For the default data set name and the SET DEFAULT LISTINGS command, the EQAUEDAT user exit might modify the data set name before the file is opened. However, if a EQADEBUG DD statement is present, the EQAUEDAT user exit is not run.

How does Debug Tool locate source and listing files?

Debug Tool reads the source or listing file for a CU each time it needs to display information about that CU. While you are debugging your CU, the data set from which the file is read can change. Each time Debug Tool needs to read a source or listing file, it searches for the data set in the following order:

1. SET SOURCE command
2. SET DEFAULT LISTINGS command. If the EQAUEDAT user exit is implemented and a EQADEBUG DD statement is not specified, the data set name might be modified by the EQAUEDAT user exit.
3. if present, the EQADEBUG DD statement
4. default data set name. If the EQAUEDAT user exit is implemented and a EQADEBUG DD statement is not specified, the data set name might be modified by the EQAUEDAT user exit.

How does Debug Tool locate COBOL side files?

Debug Tool might read from a COBOL side file more than once but it always reads the side file from the same data set. After Debug Tool locates a valid side file, you cannot direct Debug Tool to a different side file. When the CU first appears, Debug Tool looks for the side file in the following order:

1. SET SOURCE command
2. default data set name. If the EQAUEDAT user exit is implemented and a EQADEBUG DD statement is not specified, the data set name might be modified by the EQAUEDAT user exit.
3. SET DEFAULT LISTINGS command. If the EQAUEDAT user exit is implemented and a EQADEBUG DD statement is not specified, the data set name might be modified by the EQAUEDAT user exit.
4. if present, the EQADEBUG DD statement

The SET SOURCE command can be entered only after the CU name appears as a CU and the side file is not found in any of the other locations. The SET DEFAULT LISTINGS command can be entered at any time before the CU name appears as a CU or, if the side file is not found in any of the other possible locations, it can be entered later.

How does Debug Tool locate EQALANGX files

An EQALANGX file, which contains debug information for an assembler or OS/VS COBOL program, might be read more than once but it is always read from the same data set. After Debug Tool locates a valid EQALANGX file, you cannot direct Debug Tool to a different EQALANGX file. After you enter the LOADDEBUGDATA (LDD) command (which is run immediately or run when the specified CU becomes known to Debug Tool), Debug Tool looks for the EQALANGX file in the following order:

1. SET SOURCE command
2. a previously loaded EQALANGX file that contains a CSECT that matches the name and length of the program
3. default data set name. If the EQAUEDAT user exit is implemented and a EQADEBUG DD statement is not specified, the data set name might be modified by the EQAUEDAT user exit.
4. SET DEFAULT LISTINGS command. If the EQAUEDAT user exit is implemented and a EQADEBUG DD statement is not specified, the data set name might be modified by the EQAUEDAT user exit.
5. the EQADEBUG DD statement

The SET SOURCE command can be entered during any of the following situations:

- Any time after the CU name appears as a disassembly CU.
- If the CU is known when the LDD command is entered but then Debug Tool does not find the EQALANGX file.
- If the CU is not known to Debug Tool when the LDD command is entered and then Debug Tool runs the LDD after the CU becomes known to Debug Tool.

The SET DEFAULT LISTINGS command can be entered any time before you enter the LDD command or, if the EQALANGX file is not found by the LDD command, after you enter the LDD command.

Appendix C. Examples: Preparing programs and modifying setup files with Debug Tool Utilities

These examples show you how to use Debug Tool Utilities to prepare your programs and how to create, manage, and use a setup file. The examples guide you through the following tasks:

1. Creating personal data sets with the correct attributes.
2. Starting Debug Tool Utilities.
3. Compiling or assembling your program by using Debug Tool Utilities. You must have Debug Tool Utilities and Advanced Functions installed on your system to run the steps in this task. If you do not have this product installed, you can build your program through your usual methods and resume this example with the next step.
4. Modifying and using a setup file to run your program in the foreground or in batch.

Creating personal data sets

Create the data sets with the names and attributes described below. Allocate 5 tracks for each of the data sets. Partitioned data sets should be specified with 5 blocks for the directory.

Table 7. Names and attributes to use when you create your own data sets.

Data set name	LRECL	BLKSIZE	RECFM	DSORG
<i>prefix</i> .SAMPLE.COBOL	80	*	FB	PO
<i>prefix</i> .SAMPLE.PLI	80	*	FB	PO
<i>prefix</i> .SAMPLE.C	80	*	FB	PO
<i>prefix</i> .SAMPLE.ASM	80	*	FB	PO
<i>prefix</i> .SAMPLE.DTSF	1280	*	VB	PO
* You can use any block size that is valid.				

Copy the following members of the *hlq*.SEQASAMP data set into the personal data sets you just created:

SEQASAMP member name	Your sample data set	Description of member
EQAWPP1	<i>prefix</i> .SAMPLE.COBOL(WPP1)	COBOL source code
EQAWPP3	<i>prefix</i> .SAMPLE.PLI(WPP3)	PL/I source code
EQAWPP4	<i>prefix</i> .SAMPLE.C(WPP4)	C source code
EQAWPP5	<i>prefix</i> .SAMPLE.ASM(WPP5)	Assembler source code
EQAWSU1	<i>prefix</i> .SAMPLE.DTSF(WSU1)	setup file for EQAWPP1
EQAWSU3	<i>prefix</i> .SAMPLE.DTSF(WSU3)	setup file for EQAWPP3
EQAWSU4	<i>prefix</i> .SAMPLE.DTSF(WSU4)	setup file for EQAWPP4
EQAWSU5	<i>prefix</i> .SAMPLE.DTSF(WSU5)	setup file for EQAWPP5

Starting Debug Tool Utilities

To start Debug Tool Utilities, do one the following options:

- If Debug Tool Utilities was installed as an option on an existing ISPF panel, then select that option.
- If Debug Tool Utilities data sets were installed as part of your log on procedure, enter the following command from ISPF option 6:

EQASTART

- If Debug Tool Utilities was installed as a separate application, enter the following command from ISPF option 6:

EX 'hlq.SEQAEXEC(EQASTART)'

The Debug Tool Utilities primary panel (EQA@PRIM) is displayed. On the command line, enter the PANELID command. This command displays the name of each panel on the upper left corner of the screen. These names are used as navigation aids in the instructions provided in this section. After you complete these examples, you can stop the display of these names by entering the PANELID command.

Compiling or assembling your program by using Debug Tool Utilities

To do the steps in this task, you must have Debug Tool Utilities and Advanced Functions installed on your system. To compile your program, do the following steps:

1. In panel EQA@PRIM, select 1. Press Enter.
2. In panel EQAPP, select one of the following option and then press Enter.
 - 1 to compile a COBOL program.
 - 3 to compile a PL/I program
 - 4 to compile a C or C++ program
 - 5 to assemble an assembler program
3. One of the following panels is displayed, depending on the language you selected in step 2:
 - EQAPPC1 for COBOL programs. Enter the following information in the fields indicated:
 - Project = *prefix*
 - Group= SAMPLE
 - Type=COBOL
 - Member=WPP1
 - EQAPPC3 for PL/I programs.
 - Project = *prefix*
 - Group= SAMPLE
 - Type=PLI
 - Member=WPP3
 - EQAPPC4 for C and C++ programs.
 - Project = *prefix*
 - Group= SAMPLE
 - Type=C
 - Member=WPP4
 - EQAPPC5 for assembler programs.

- Project = *prefix*
 - Group= SAMPLE
 - Type=ASM
 - Member=WPP5
4. If you are preparing an assembler program, enter the location of your CEE library in the Syslib data set Name field. For example: 'CEE.SCEEMAC'
 5. Enter '/' to edit options and specify a naming pattern for the output data sets in the field Data set naming pattern. Press Enter.
 6. One of the following panels is displayed, depending on the language you selected in step 2 on page 328:
 - EQAPPC1A for COBOL programs.
 - EQAPPC3A for PL/I programs.
 - EQAPPC4A for C and C++ programs.
 - EQAPPC5A for assembler programs.

Look at the panel to review the following information:

 - test compiler options
 - naming patterns for output data sets

Press PF3 (Exit).
 7. One of the following panels is displayed, depending on the language you selected in step 2 on page 328:
 - EQAPPC1 for COBOL programs.
 - EQAPPC3 for PL/I programs.
 - EQAPPC4 for C and C++ programs.
 - EQAPPC5 for assembler programs.

Select "F" to process these programs in the foreground. Specify "N" for CICS translator and "N" for DB2 precompiler. None of these programs contain CICS or DB2 instructions. Press Enter.
 8. One of the following panels is displayed, depending on the language you selected in step 2 on page 328:
 - EQAPPC1B for COBOL programs.
 - EQAPPC3B for PL/I programs.
 - EQAPPC4B for C and C++ programs.
 - EQAPPC5B for assembler programs.

Make a note of the data set name for Object compilation output. For a COBOL program, the data set name will look similar to the following name: *prefix*.SAMPLE.OBJECT(WPP1). You will use this name when you link your object modules. Press Enter.
 9. If panel EQAPPA1 is displayed, press Enter.
 10. One of the following panels is displayed, depending on the language you selected in step 2 on page 328:
 - EQAPPC1C for COBOL programs.
 - EQAPPC3C for PL/I programs.
 - EQAPPC4C for C and C++ programs.
 - EQAPPC5C for assembler programs.

Check for a 0 or 4 return code. Type a "b" in the Listing field. Press Enter.

11. In panel ISRBROBA, browse the file to review the messages. When you are done reviewing the messages, press PF3 (Exit).
12. One of the following panels is displayed, depending on the language you selected in step 2 on page 328:
 - EQAPPC1C for COBOL programs.
 - EQAPPC3C for PL/I programs.
 - EQAPPC4C for C and C++ programs.
 - EQAPPC5C for assembler programs.
 Press PF3 (Exit).
13. One of the following panels is displayed, depending on the language you selected in step 2 on page 328:
 - EQAPPC1B for COBOL programs.
 - EQAPPC3B for PL/I programs.
 - EQAPPC4B for C and C++ programs.
 - EQAPPC5B for assembler programs.
 Press PF3 (Exit).
14. One of the following panels is displayed, depending on the language you selected in step 2 on page 328:
 - EQAPPC1 for COBOL programs.
 - EQAPPC3 for PL/I programs.
 - EQAPPC4 for C and C++ programs.
 - EQAPPC5 for assembler programs.
 Press PF3 (Exit).
15. In panel EQAPP, press PF3 (Exit) to return to EQA@PRIM panel.

To link your object modules, do the following steps:

1. In panel EQA@PRIM, select 1. Press Enter.
2. In panel EQAPP, select L. Press Enter.
3. In panel EQAPPCL, specify "F" to process the programs in the foreground. Then, choose one of the following options, depending on the language you selected in step 2 on page 328:
 - For the COBOL program, use the following values for each field: Project = *prefix*, Group= SAMPLE, Type=OBJECT, Member=WPP1
 - For the PL/I program, use the following values for each field: Project = *prefix*, Group= SAMPLE, Type=OBJECT, Member=WPP3
 - For the C program, use the following values for each field: Project = *prefix*, Group= SAMPLE, Type=OBJECT, Member=WPP4
 - For the assembler program, use the following values for each field: Project = *prefix*, Group= SAMPLE, Type=OBJECT, Member=WPP5
4. In panel EQAPPCL, specify the name of the other libraries you need to link to your program. For example, in the field Syslib data set Name, specify the prefix of your CEE library: 'CEE.SCEELKED'. Press Enter.
5. In panel EQAPPCLB, make a note of the data set name in the Load link-edit output field. You will use this name when you modify a setup file. Press Enter.
6. If panel EQAPPA1 is displayed, press Enter.
7. In panel EQAPPCLC, check for a 0 return code. Type a "V" in the Listing field. Press Enter.

8. In panel ISREDDE2, review the messages. After you review the messages, press PF3 (Exit).
9. In panel EQAPPCLC, press PF3 (Exit).
10. In panel EQAPPCLB, press PF3 (Exit).
11. In panel EQAPPCL, press PF3 (Exit).
12. In panel EQAPP, press PF3 (Exit) to return to EQA@PRIM panel.

Modifying and using a setup file

This example describes how to modify a setup file and then use it to run the examples in the TSO foreground or run the examples in the background by submitting a MVS batch job.

Run the program in foreground

To modify and run the setup file so your program runs in the foreground, do the following steps:

1. In panel EQA@PRIM, select 2. Press Enter.
2. In panel EQAPFOR, select one of the following choices, depending on which language you selected in step 2 on page 328:
 - For the COBOL program, use the following values for each field: Project = *prefix*, Group= SAMPLE, Type=DTSF, Member = WSU1
 - For the PL/I program, use the following values for each field: Project = *prefix*, Group = SAMPLE, Type=DTSF, Member=WSU3
 - For the C program, use the following values for each field: Project = *prefix*, Group= SAMPLE, Type=DTSF, Member=WSU4
 - For the assembler program, use the following values for each field: Project = *prefix*, Group= SAMPLE, Type=DTSF, Member=WSU5Press Enter.
3. In panel EQAPFORS, do the following steps:
 - a. Replace &LOADDS. with the name of the load data set from step 5 on page 330 of instructions on how to link the object modules.
 - b. Replace &EQAPRFX. with the prefix your EQAW (Debug Tool) library.
 - c. Replace &CEEPRFX. with the prefix your CEE (Language Environment) library.
 - d. Enter "e" in Cmd field next to CMDS DD name. In the window that is displayed, if there is a QUIT ; statement at the end of the data set, remove it. Press PF3 (Exit).
 - e. Type "run" in command line. Press Enter.
4. Debug Tool is started and the Debug Tool window is displayed. Enter any valid Debug Tool commands to verify that you can debug the program. Enter "qq" in the command line to stop Debug Tool and close the Debug Tool window.
5. In panel EQAPFORS, check the return code message:
 - For the COBOL program, the return code (RC) is 0.
 - For the PL/I program, the return code (RC) is 1000.
 - For the C program, the return code (RC) is 0.
 - For the assembler program, the return code (RC) is 0.Press PF3 (Exit). All the changes made to the setup file are saved.
6. In panel EQAPFOR, press PF3 (Exit) to return to the panel EQA@PRIM.

Run the program in batch

To modify and run the setup file so that the program runs in batch, do the following steps:

1. In panel EQA@PRIM, select 0. Press Enter.
2. In panel EQAPDEF, review the job card information. If there are any changes that need to be made, make them. Press PF3 (Exit).
3. In panel EQA@PRIM, select 2. Press Enter.
4. In panel EQAPFOR, select one of the following choices, depending on which language you selected in step 2 on page 328:
 - For the COBOL program, use the following values for each field: Project = *prefix*, Group = SAMPLE, Type = DTSF, Member = WSU1
 - For the PL/I program, use the following values for each field: Project = *prefix*, Group = SAMPLE, Type = DTSF, Member = WSU3
 - For the C program, use the following values for each field: Project = *prefix*, Group = SAMPLE, Type = DTSF, Member = WSU4
 - For the assembler program, use the following values for each field: Project = *prefix*, Group = SAMPLE, Type = DTSF, Member = WSU5

Press Enter.

5. If you ran the steps beginning on page 331 (running the program in foreground), you can skip this step. In panel EQAPFORS, do the following steps:
 - a. Replace &LOADDS. with the name of the load data set from step 5 on page 330 of instructions on how to link the object modules.
 - b. Replace &EQAPRFX. with the prefix your EQAW (Debug Tool) library.
 - c. Replace &CEEPRFX. with the prefix your CEE (Language Environment) library.
6. Enter "e" in the Cmd field next to CMDSD DD name. If there is not 'QUIT ;' statement at the end of the data set, then add the statement. Press PF3 (Exit).
7. Type submit in command line. Press Enter.
8. In panel ISREDDE2, type submit in the command line. Press Enter. Make a note of the job number that is displayed.
9. In panel ISREDDE2, press PF3 (Exit).
10. In panel EQAPFORS, press PF3 (Exit). The changes you made to the setup file are saved.
11. In panel EQAPFOR, press PF3 (Exit) to return to EQA@PRIM panel. locate the job output using the job number recorded. Check for zero return code and the command log output at the end of the job output.

Appendix D. Notes on debugging in batch mode

Debug Tool can run in batch mode, creating a noninteractive session.

In batch mode, Debug Tool receives its input from the primary commands file, the USE file, or the command string specified in the TEST run-time option, and writes its normal output to a log file.

Note: You must ensure that you specify a log data set.

Commands that require user interaction, such as PANEL, are invalid in batch mode.

You might want to run a Debug Tool session in batch mode if:

- You want to restrict the processor resources used. Batch mode generally uses fewer processor resources than interactive mode.
- You have a program that might tie up your terminal for long periods of time. With batch mode, you can use your terminal for other work while the batch job is running.
- You are debugging an application in its native batch environment, such as MVS/JES or CICS batch.

When Debug Tool is reading commands from a specified data set or file and no more commands are available in that data set or file, it forces a GO command until the end of the program is reached.

When debugging in batch mode, use QUIT to end your session.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

“Starting Debug Tool in batch mode” on page 91

Appendix E. Notes on debugging in remote debug mode

Debug Tool can run in remote debug mode, by using TCP/IP to connect to a remote debugger installed on your workstation. The following remote debuggers can be used:

- IBM Distributed Debugger (also known as VisualAge Remote Debugger)
- Compiled Language Debugger component of WebSphere Studio Enterprise Developer

These remote debuggers support single and multiple connection types, except for earlier versions of the IBM Distributed Debugger. If you are using a version of IBM Distributed Debugger that is earlier than version 9.2 (copyright date 2003/10/19), you must specify multiple connection type.

Specifying a single connection type is recommended because it uses less resource and avoids security problems when you use a firewall. You specify single connection type by using the TCPIP& of the TEST run-time option. You specify multiple connection type by using the VADTCPIP& suboption of the TEST run-time option.

When you specify the TCPIP& or VADTCPIP& suboption, you must specify the port number that the remote debugger is using to listen for a debug session. By default, IBM Distributed Debugger uses port 8000 and the Compiled Language Debugger component of WebSphere Studio Enterprise Developer uses port 8001.

When you use remote debug mode, consider the following possible errors:

- The `tcpip_workstation_id` or `port_id` parameters must be syntactically and functionally correct. If they are not and you try to start a remote debug mode session, Debug Tool starts a full-screen mode session. For example, if you try to start a remote debug mode session from TSO or a CICS program by using incorrect parameters, a full-screen mode session is displayed on your 3270 type terminal. This error is recorded in the MVS SDSF log as an *allocation* failure.
- If the `tcpip_workstation_id` or `port_id` parameters are not syntactically and functionally correct and you try to debug batch program, Debug Tool terminates and the batch program runs as though no debug session was started. This error occurs when, for example, you run a JES batch job or CICS batch transaction. This error is recorded in the MVS SDSF log as an *allocation* failure.
- If your z/OS or OS/390 environment is not using the default TCP/IP data set named TCPIP.TCPIP.DATA and you try to start a remote debug mode session to debug a batch program, Debug Tool terminates. The batch program runs as though no debug session was started. This error is recorded in the MVS SDSF log as an *allocation* error.

To fix this error, specify the SYSTCPD DDNAME with the appropriate TCP/IP data set name. For example,

```
//SYSTCPD DD DISP=SHR,DSN=MY.TCPIP.DATA
```

- For TCP/IP sessions, the remote debug daemon must be started at the workstation before you start Debug Tool. Refer to the remote debugger information for help on using the remote debug daemon.

Debug Tool commands supported in remote debug mode

The following table summarizes the commands available to each remote debugger:

Command	Compiled Language Debugger component of WebSphere Studio Enterprise Developer	IBM Distributed Debugger
CALL %VER	X	X
DESCRIBE CUS	X	X
LOADDEBUGDATA (for assembler only)	X	
SET ASSEMBLER	X	
SET AUTOMONITOR	X	
SET DISASSEMBLY	X	X
SET DYNDEBUG	X	X
SET LOG	X	X
SET WARNING	X	X

See *Debug Tool for z/OS Reference and Messages* for more information about each command.

Tip on monitoring variables in optimized COBOL program

After you start the remote debugger and start your optimized COBOL program, do the following steps:

1. Step into your program by using the Step Into button.
2. Monitor a variable. The variable's name and current value are displayed in the Monitor window.
3. Step through your program until you reach a statement that alters the value of the variable you are monitoring. If you attempt to run the statement, a Debugger Message window displays the following message:

Error occurred: EQA2421E The assignment was not performed because the assigned value might not be used by the program, due to optimization.

4. Enter the SET WARNING OFF command in the input line of the Command Log window. The Command Log window displays a message that the SET WARNING OFF command was received.
5. Step through the statement. A Debugger Message window displays the following message:

Error occurred: EQA2420W The assignment was performed but the assigned value might not be used by the program, due to optimization.

The new value of the variable you are monitoring is displayed in the Monitors window.

Appendix F. Syntax of the TEST Compiler option

Debug Tool allows you to debug applications written in C, C++, COBOL, and PL/I. In order to debug your applications, you must compile them with the TEST compiler option. If you do not compile your applications with the TEST option, then you can debug them only by using the disassembly view.

This chapter describes the TEST compiler option for C, C++, COBOL, and PL/I. For more information on how to use the compiler options, refer to the chapters in Part 2, “Preparing your program for debugging,” on page 19. For a listing of all the compiler options available for each programming language, see the documentation provided with each programming language compiler.

The suboptions of the TEST compiler option control the generation of symbol tables and program hooks that Debug Tool needs to debug your programs. The choices that you make when compiling your program affect the amount of Debug Tool function available during your debug session. When a program is under development, you should compile the program with TEST(ALL) to get the full capability of Debug Tool.

Refer to the following sections for more information related to the material discussed in this section.

Related tasks

z/OS C/C++ User's Guide

z/OS C/C++ Programming Guide

COBOL for OS/390 & VM Programming Guide

Enterprise COBOL for z/OS and OS/390 Programming Guide

VisualAge PL/I for OS/390 Programming Guide

Enterprise PL/I for z/OS and OS/390 Programming Guide

Related references

C/C++ Language Reference

COBOL for OS/390 & VM Language Reference


Enterprise COBOL for z/OS and OS/390 Language Reference

Enterprise PL/I for z/OS and OS/390 Language Reference

VisualAge PL/I Language Reference

Syntax for the C TEST compiler option

The syntax for the C TEST compiler option is:



The following list explains what is produced by each option and suboption and how Debug Tool uses the information when you debug your program:

NOTEST

Specifies that no debugging information is to be generated. That is, no hooks are compiled into your program, no symbol tables are created, and Debug Tool does not have access to any symbol information.

- You cannot step through program statements. You can suspend execution of the program only at the initialization of the main compile unit.
- You cannot examine or use any program variables.
- You can list storage and registers.
- You cannot use the Debug Tool command GOTO.

TEST

Produces debugging information for Debug Tool to use during debugging. The extent of the information provided depends on which suboptions are selected.

The following restrictions apply when using TEST:

- The maximum number of lines in a single source file cannot exceed 131,072.
- The maximum number of include files that have executable statements cannot exceed 1024.

BLOCK

Inserts hooks only at block entry and exit points into your program's object. A block is any number of data definitions, declarations, or statements enclosed within a single set of braces. BLOCK also creates hooks for nested blocks. If the SYM suboption is specified, symbol tables are generated for variables local to these nested blocks.

- You can only gain control at entry and exit points of blocks.
- Issuing a command such as STEP causes your program to run until it reaches the exit point.

NOBLOCK

Prevents symbol information and hooks from being generated for nested blocks.

LINE

Hooks are generated at most executable statements. Hooks are not generated for:

- Lines that identify blocks (lines containing braces)
- Null statements
- Labels

NOLINE

Suppresses the generation of hooks at statements (line numbers).

PATH

Hooks are generated at all path points (if-then-else, calls, etc.)

- This option does not influence the generation of hooks at entry and exit points for nested blocks. The BLOCK suboption must be specified if such hooks are desired.
- Debug Tool can gain control only at path points and block entry and exit points. If you attempt to step through your program, Debug Tool gains control only at statements that coincide with path points, giving the appearance that not all statements are executed.
- The Debug Tool command GOTO is valid only for statements and labels coinciding with path points.

NOPATH

No hooks are generated at path points.

SYM

Generates symbol tables in the program's object which give Debug Tool access to variables and other symbol information.

- You can reference all program variables by name, allowing you to examine them or use them in expressions.
- You can use the Debug Tool command GOTO to branch to a label (paragraph or section name).

NOSYM

Suppresses the generation of symbol tables. Debug Tool does not have access to any symbol information.

- You cannot reference program variables by name.
- You cannot use commands such as LIST or DESCRIBE to access a variable or expression.
- You cannot use commands such as CALL or GOTO to branch to another label (paragraph or section name).

ALL

Hooks are inserted and a symbol table is generated. Hooks are generated at all statements, all path points (if-then-else, calls, and so on), and at all function entry and exit points.

ALL is equivalent to TEST(LINE, BLOCK, PATH, SYM).

NONE

Generates hooks only at function entry and exit points. Hooks at block and line points are not inserted, and the symbol tables are suppressed.

TEST(NONE) is equivalent to TEST(NOLINE, NOBLOCK, NOPATH, NOSYM).

Syntax for the C++ TEST compiler option

The syntax for the C++ TEST compiler option is:



Notes:

- 1 The HOOK and NOHOOK options are available only with OS/390 C/C++, Version 2 Release 4, or later.

The following list explains what is produced by each option and how Debug Tool uses them when debugging your program:

NOTEST

Specifies that no debugging information is to be generated. That is, no hooks are compiled into your program, no symbol tables are created, and Debug Tool does not have access to any symbol information.

- You cannot step through program statements. You can suspend execution of the program only at the initialization of the main compile unit.
- You cannot examine or use any program variables.
- You can list storage and registers.
- You cannot use the Debug Tool command GOTO.

TEST

Produces debugging information for Debug Tool to use during debugging. The following restrictions apply when using the TEST option:

- The maximum number of lines in a single source file cannot exceed 131,072.
- The maximum number of include files that have executable statements cannot exceed 1024.

HOOK


Generates some or all possible hook information, depending on NOOPT or OPT. This option is only available on Version 2, Release 4 C and C++ or later.

NOHOOK

No hook information is generated. This option is available only with OS/390 C/C++, Version 2 Release 4, or later.

Syntax for the COBOL TEST compiler option

The syntax for the COBOL TEST compiler option is:



Notes:

- 1 The SEPARATE and NOSEPARATE suboptions are available for programs compiled only with Enterprise COBOL for z/OS and OS/390 or COBOL for OS/390 & VM compilers.

The TEST compiler suboptions control the production of debugging information such as symbol tables and hooks that Debug Tool needs to debug your program. The suboptions you choose can affect the size of your load module:

- To get the full capabilities of Debug Tool, compile your program with TEST(ALL,SYM).
- To get most of the capabilities of Debug Tool and a smaller load module, compile your programs with TEST(NONE,SYM,SEPARATE). You can then use the Dynamic Debug facility to debug your program.

If you compile your program with the TEST or NOTEST options and their corresponding suboptions, Debug Tool can do the following:

NOTEST

Specifies that no debug information is to be generated: no hooks are compiled into your program, no symbol tables are created, and Debug Tool does not have access to any symbol information. Using NOTEST produces the following results:

- You cannot step through program statements.
- You can suspend execution of the program only at the initialization of the main compile unit.
- You can include calls to CEETEST in your program to allow you to suspend program execution and issue Debug Tool commands.
- You cannot examine or use any program variables.
- You can list storage and registers.
- The source listing produced by the compiler cannot be used; therefore, no listing is available during a debug session. Using the SET DEFAULT LISTINGS command can not make a listing available.
- Because a statement table is not available, you cannot set any statement breakpoints or use commands such as GOTO or QUERY location.

TEST

Produces debugging information for Debug Tool to use during debugging. The extent of the information provided depends on which of the following suboptions are selected.

ALL

Generates all hooks, including hooks at all statement, path, date processing, and program entry and exit points. If you use this suboption, the size of your program increases significantly.

- The COBOL compiler only generates hooks for date processing statements when the DATEPROC compiler option is specified. A date processing statement is any statement that references a date field, or any EVALUATE or SEARCH statement WHEN phrase that references a date field.
- You can set breakpoints at all statements and path points, and step through your program.
- Debug Tool can gain control of the program at all statements, path points, date processing statements, labels, and block entry and exit points, allowing you to enter Debug Tool commands.

- Branching to statements and labels using the Debug Tool command GOTO is allowed.

BLOCK

Hooks are inserted at all block entry and exit points.

- Debug Tool gains control at entry and exit of your program, methods, and nested programs.
- Debug Tool can be explicitly started at any point with a call to CEETEST.
- Issuing a command such as STEP causes your program to run until it reaches the next entry or exit point.
- GOTO can be used to branch to statements that coincide with block entry and exit points.

NONE

No hooks are inserted in the program.

- You can use the GOTO command only if the program is compiled with one of the following compilers:
 - Enterprise COBOL for z/OS and OS/390
 - COBOL for OS/390 & VM
- A call to CEETEST can be used at any point to start Debug Tool.

PATH

Hooks are inserted at all path points and at all program entry and exit points. A path point is anywhere in a program where the logic flow is not necessarily sequential or can change. Some examples of path points are IF-THEN-ELSE constructs, PERFORM loops, ON SIZE ERROR phrases, and CALL statements.

- Debug Tool can gain control only at path points and block entry and exit points. If you attempt to step through your program, Debug Tool gains control only at statements that coincide with path points, giving the appearance that not all statements are executed.
- A call to CEETEST can be used at any point to start Debug Tool.
- The Debug Tool command GOTO is valid for all statements and labels coinciding with path points.

STMT

Hooks are inserted at every statement and label, at every date processing statement, and at all entry and exit points.

- The COBOL compiler generates compiled-in hooks for date processing statements only when the DATEPROC compiler option is specified. A date processing statement is any statement that references a date field, or any EVALUATE or SEARCH statement WHEN phrase that references a date field.
- You can set breakpoints at all statements and step through your program.
- Debug Tool cannot gain control at path points unless they are also at statement boundaries.
- Branching to all statements and labels using the Debug Tool command GOTO is allowed.

SYM

Generates symbol tables in the program's object that give Debug Tool access to variables and other symbol information.

- You can reference all program variables by name, which allows you to examine them or use them in expressions.

- You can use the PLAYBACK ENABLE command with the DATA parameter.
- You can use the SET AUTOMONITOR ON command.
- SYM is required to support labels (paragraph or section names) as GOTO targets.

SEPARATE

Saves the symbolic table information in a separate debug file. This suboption is available only if you compile with the following compilers:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298

NOSEPARATE

The symbolic table information is stored in the object. NOSEPARATE is the default. This suboption is available only if you compile with the following compilers:

- Enterprise COBOL for z/OS and OS/390, Version 3
- COBOL for OS/390 & VM, Version 2 Release 2
- COBOL for OS/390 & VM, Version 2 Release 1 with APAR PQ40298

NOSYM

Suppresses the generation of dictionary tables. Debug Tool does not have access to any symbol information. Using NOSYM produces the following results:

- You cannot reference program variables by name.
- You cannot use commands such as LIST or DESCRIBE to access a variable or expression.
- You cannot use commands such as CALL variable to branch to another program, or GOTO to branch to another label (paragraph or section name).

Specifying TEST with no suboptions is equivalent to TEST(ALL, SYM, NOSEPARATE).

Refer to the following sections for more information related to the material discussed in this section.

Related references


Debug Tool for z/OS Reference and Messages

Enterprise COBOL for z/OS and OS/390 Programming Guide


COBOL for OS/390 & VM Programming Guide

Syntax for the PL/I and Enterprise PL/I TEST compiler options

The syntax for the PL/I TEST compiler option is:



The syntax for the Enterprise PL/I TEST compiler option is:



The following list explains each option and suboption and the capabilities of Debug Tool when your program is compiled using these options:

NOTEST

Specifies that no debugging information is generated: no hooks are compiled into your program, no dictionary tables are created, and Debug Tool does not have access to any symbol information. Using NOTEST produces the following results:

- You can list storage and registers.
- You can include calls to PLITEST or CEETEST in your program so you can suspend running your program and issue Debug Tool commands.
- You cannot step through program statements. You can suspend running your program only at the initialization of the main compile unit.
- You cannot examine or use any program variables.
- Because hooks at the statement level are not inserted, you cannot set any statement breakpoints or use commands such as GOTO or QUERY LOCATION.
- The source listing produced by the compiler cannot be used; therefore, no listing is available during a debug session.

TEST

Produces debugging information for Debug Tool to use during debugging. The extent of the information provided depends on which of the following suboptions are selected:

ALL

Generates all compiled-in hooks, including all statement, path, and program entry and exit hooks.

- You can set breakpoints at all statements and path points, and STEP through your program.
- Debug Tool can gain control of the program at all statements, path points, labels, and block entry and exit points, allowing you to enter Debug Tool commands.
- Enables branching to statements and labels using the Debug Tool command GOTO.

BLOCK

Hooks are inserted at all block entry and exit points.

- Enables Debug Tool to gain control at block boundaries: block entry and block exit.
- You can gain control only at entry and exit points of your program and all entry and exit points of internal program blocks.
- A call to PLITEST or CEETEST can be used to start Debug Tool at any point in your program.
- Issuing a command such as STEP causes your program to run until it reaches the next block entry or exit point.
- Hooks are not inserted into an empty ON-unit or an ON-unit consisting of a single GOTO statement.

NONE

No hooks are inserted in the program.

- A call to PLITEST or CEETEST can be used to start Debug Tool at any point in your program.

PATH

Hooks are inserted at all path points:

- Before the THEN part of an IF statement.
- Before the ELSE part of an IF statement.
- Before the first statement of all WHEN clauses of a SELECT-group.
- Before the OTHERWISE statement of a SELECT-group.
- At the end of a repetitive DO statement, just before the Do-group is to be executed.
- At every CALL or function reference, both before and after control is passed to the routine.
- Before the statement following a user label, excluding labeled FORMAT statements. If a statement has multiple labels, only one hook is inserted.

Specifying PATH also causes BLOCK hooks to be inserted.

STMT

Hooks are inserted before most executable statements and labels. STMT also causes BLOCK hooks to be inserted.

- You can set breakpoints at all statements and step through your program.
- Debug Tool cannot gain control at path points unless they are also at statement boundaries.
- Branching to all statements and labels using the Debug Tool command GOTO is allowed.

SYM

Generates a symbol table in the program's object file. The symbol table is required for examining program variables or program control constants by name.

- You can reference all program variables by name, which allows you to examine them or use them in expressions and use the DATA parameter of the PLAYBACK ENABLE command.
- Enables support for the SET AUTOMONITOR ON command.
- Enables the support for labels as GOTO targets.

NOSYM

Suppresses the generation of a symbol table. Debug Tool does not have access to any symbol information that causes the following results:

- You cannot reference program variables by name.
- You cannot use commands such as LIST or DESCRIBE to access a variable or expression.
- You cannot use commands such as CALL variable to branch to another program, or GOTO to branch to another label (procedure or block name).

HOOK (Enterprise PL/I for z/OS, Version 3 Release 4, only)

Causes the compiler to insert hooks into the generated code if any of the TEST suboptions ALL, STMT, BLOCK or PATH are in effect.

NOHOOK (Enterprise PL/I for z/OS, Version 3 Release 4, only)

Causes the compiler not to insert hooks in to the generated code.

For Debug Tool to generate overlay hooks, one of the suboptions ALL, PATH, STMT or BLOCK must be in effect, but HOOK need not be specified, and NOHOOK would be recommended.

If NOHOOK is specified, ENTRY and EXIT breakpoints are the only PATH breakpoints at which Debug Tool stops.

Compiling with TEST(STMT), TEST(PATH), or TEST(ALL) causes a statement number table to be generated. If the STMT compiler option is in effect, specifying TEST causes the GOSTMT compiler option to be in effect. If the NUMBER compiler option is in effect, specifying TEST causes the GONUMBER compiler option to be in effect.

Refer to the following sections for more information related to the material discussed in this section.

Related references

PL/I for MVS and VM Programming Guide

VisualAge PL/I for OS/390 Programming Guide

Enterprise PL/I for z/OS and OS/390 Programming Guide

Appendix G. Debug Tool Load Module Analyzer

The Debug Tool Load Module Analyzer analyzes MVS load modules or program objects to determine the language translator (compiler or assembler) used to generate the object for each CSECT. This program can process all or selected load modules or program objects in a concatenation of PDS or PDSE data sets. To use the Load Module Analyzer, you must purchase and install Debug Tool Utilities and Advanced Functions Version 5.1 (5655-M19) with the PTF for APAR PK07204.

Choosing a starting method

You can start the Load Module Analyzer in one of the following ways:

- Editing sample JCL provided in member EQAZLMA of data set *hlq.SEQASAMP*, then submitting the JCL to run as a batch job.
- By selecting option 5 of Debug Tool Utility ISPF panel.

Starting the Load Module Analyzer by using JCL

To start the Load Module Analyzer by using sample JCL, do the following steps:

1. Make a copy of member EQAZLMA in data set *hlq.SEQASAMP*.
2. Edit that copy, as instructed in the member.
3. Submit the JCL.
4. Review the results.

Starting the Load Module Analyzer by using Debug Tool Utilities

To start the Load Module Analyzer by using Debug Tool Utilities, do the following steps:

1. Start Debug Tool Utilities.
2. Select option 5.
3. Enter the appropriate information into each field on the panel, keeping in mind the following behavior:
 - If you specify that you want a single load module or program object analyzed, Load Module Analyzer is run in the TSO foreground.
 - If you specify that you want an entire PDS or PDSE analyzed, JCL is generated to start Load Module Analyzer in MVS batch. Then, you must submit or save the generated JCL.

Description of the JCL

By default, the Load Module Analyzer program processes all members in the PDS or PDSE specified in the EQALIB DD statement. You can use control statements to instruct Load Module Analyzer to process only specific members of the data set concatenation.

Description of DD names

Load Module Analyzer uses the following DD names:

EQALIB

Specifies a concatenation of PDS or PDSE data sets containing the load

modules or program objects to be analyzed. If the same member is present in more than one of the concatenated data sets, only the first member is processed.

EQAPRINT

Specifies the output report. It can be in fixed block record format (RECFM=FBA) with a logical record length of 133 or more (LRECL >=133) or in variable block record format (RECF=VBA) with a logical record length of 137 or more (LRECL >= 137).

EQAIN

Specifies the control statements. If you want only specific load modules or program objects to be processed, use the following syntax:

```
SELECT MEMBER=load_module_name
```

If you want all load modules to be processed, you can omit this DD statement, direct it to DUMMY, or direct it to empty data set. This file must be in fixed block record format (RECFM=FB) with a logical record length of 80 (LRECL=80). Each control statement must be on a separate line. The entries are free-form and you can use blanks before or after each keyword and operator. You can include comments by placing an asterisk in column 1.

EQASYSPPF

Specifies a list of system prefixes. This is a list of prefixes of names of CSECTs that you want Load Module Analyzer to recognize as system routines. The list helps limit the amount of output displayed for these prefixes. This file must be in fixed block record format (RECFM=FB) with a logical record length of 80 (LRECL=80). Debug Tool provides data for this file in member EQALMPFX of the table library (SEQATLIB). See "Description of EQASYSPPF file format" on page 349 for a description of this file.

EQAPGMNM

Specifies a list of program names corresponding to program IDs found in the load module IDR data. This file must be in fixed block record format (RECFM=FB) with a logical record length of 80 (LRECL=80). Debug Tool provides data for this file in member EQALMPGM of the table library (EQATLIB). See "Description of EQAPGMNM file format" on page 350 for directions on how to add entries to this list.

Description of parameters

You can specify parameters by using the PARM= keyword of the EXEC JCL statement. The parameter string passed to this program can consist of any of the following parameters, separated by commas or blanks:

DATEFMT=*dateformat*

Specifies how dates are to be formatted. If a date from the binder CSECT identification record (IDR) data does not appear to be a valid Julian date, it is not reformatted. Use one of the following values:

YYYYMMDD

Sort format: YYYY/MM/DD. (Default)

MMDDYYYY

U.S. standard format: MM/DD/YYYY.

DDMMYYYY

European standard format: DD/MM/YYYY.

LOUD

Specifies that the data read from the EQASYSPF and EQAPGMNM files is displayed in the output listing.

NATLANG=*language_code*

Specifies the national language. Use one of the following values:

ENU

Mixed-case English. (Default)

UEN

Upper-case English.

JPN

Japanese.

OSVSONLY

Specifies that only CSECTs compiled with the OS/VS COBOL compiler are to be displayed in the output. Information about all other CSECTs is suppressed.

SHOWLIB

Specifies that the include indicator in the EQASYSPF file is to be ignored so that all CSECTs are listed.

SORTBY=*sort_option*

Specifies how to sort the names of the CSECTs in the output. Use one of the following values:

OFFSET

Sort by offset; the order shown in the linkage editor or AMBLIST output. (Default)

NAME

Sorts by CSECT name.

PROGRAM

Sort by the translator program ID.

LANGUAGE

Sorts by the source language and by the translator program ID.

DATE

Sorts by the translation date.

Description of EQASYSPF file format

This file contains a list of system prefixes. When Load Module Analyzer finds a CSECT that has a name prefixed by a name in this list and the entry for that prefix indicates that names beginning with that prefix are not to be included, Load Module Analyzer does not display an individual entry for that CSECT. Instead, a single line is displayed in the output for each prefix found that indicates that one or more CSECTs with the specified prefix was found.

Debug Tool supplies data for this file in member EQALMPFX of the table library (SEQATLIB). If you want to add entries to this file, create a data set containing the new entries. Then, concatenate this data set to the one that ships with Debug Tool. Concatenating the data sets prevents your entries from being deleted if an updated table member is shipped in future releases of Debug Tool.

Each line in this file represents one entry. The entries are free-form; however, each item must be separated from the previous item by one or more blanks. You can include comments by placing an asterisk in column 1. Use the following syntax for each line:

```
prefix I L description
```

prefix

A one to seven character prefix.

I Include indicator. Specify a "1" to indicate that each CSECT beginning with this prefix is to be treated as an ordinary CSECT. Specify a "0" to indicate that CSECTs beginning with this prefix are not to be listed individually.

L Language or system component indicator. Choose from one of the following characters:

B COBOL

V OS/VS COBOL

P PL/I

E Enterprise PL/I

C C/C++

A Assembler

L Language Environment

S CICS

I IMS

2 DB2

M MVS

T TCP/IP

***** Unclassified.

description

A twelve-character description of the component owning the prefix.

Description of EQAPGMNM file format

This file contains a list of program names corresponding to program IDs found in the load module IDR data. These names are used in the output to describe the language translator used to generate the object for the corresponding CSECT.

Debug Tool provides data for this file in member EQALMPGM of the table library (SEQATLIB). If you want to add entries to this file, create a data set containing the new entries. Then, concatenate this data set to the one that ships with Debug Tool. Concatenating the data sets prevents your entries from being deleted if an updated table members is shipped in future releases of Debug Tool.

Each line represents one entry. The entries are free-form. The program number must begin in column 1 and each item must be separated from the previous item by one or more blanks. You can include comments by placing an asterisk in column 1. You cannot use sequence numbers in this file. Use the following syntax for each line:

```
program_name L program_description
```

program_name

A seven character program number.

L Language or system component indicator. See “Description of EQASYSPF file format” on page 349 for a list of possible values.

program_description

A description of the program.

Description of program output

The output for each load module or program object is displayed in the following order:

- All members of the first EQALIB concatenation with each load module or program object appearing in alphabetical order
- All members of the second EQALIB concatenation that are not duplicates of members in the previous concatenation, with each load module or program object appearing in alphabetical order
- All members of the next EQALIB concatenation that are not duplicates of members in the previous concatenation, with each load module or program object appearing in alphabetical order

Alias names are displayed in the following manner:

- If the primary member name exists, this name is displayed in the output in the order previously described. Prior to the output of the contents of that member, a list of alias names for the primary member name is given.
- If the primary member name is not present in the data set, the alias is displayed the order previously described.

Description of output contents

The following information is included in the output for each CSECT:

- CSECT name
- CSECT length in hexadecimal
- Program-ID as contained in the binder IDR data
- Translator (compile or assembly) date
- Program description as supplied for the specified program ID.
- For OS/VS COBOL, PARM=RES or PARM=NORES.
 - PARM=RES indicates that one or more OS/VS COBOL CSECTs in the load module or program object were compiled with the NORES compiler option.
 - PARM=NORES indicates that all OS/VS COBOL CSECTs in the load module or program object were compiled with the NORES compiler option.

Example: Output for an OS/VS COBOL load module

The following is a fragment of output that might appear for an OS/VS COBOL load module:

```
Load Module TEST.LIBRARY.LOAD(COB010)

CSECT      Length  Program-ID  Trn-Date    Program-Description
ALIAS: ZCOB010

COB01A0      5AA  5740CB103   2004/12/02  OS/VS COBOL Version 1 Release 2, PARM=NORES
COB01B0      52E  5740CB103   2004/09/15  OS/VS COBOL Version 1 Release 2, PARM=NORES
COB01C0      5D4  5740CB103   2004/09/15  OS/VS COBOL Version 1 Release 2, PARM=NORES
COB01D0      4C6  5740CB103   2004/09/15  OS/VS COBOL Version 1 Release 2, PARM=NORES
ILB*          5734AS1              OS Assembler H
```

Appendix H. Accessibility

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, to use software products successfully. The accessibility features in z/OS provide accessibility for Debug Tool.

The major accessibility features in z/OS enable users to:

- Use assistive technology products such as screen readers and screen magnifier software
- Operate specific or equivalent features by using only the keyboard
- Customize display attributes such as color, contrast, and font size

Using assistive technologies

Assistive technology products work with the user interfaces that are found in z/OS. For specific guidance information, consult the documentation for the assistive technology product that you use to access z/OS interfaces.

Keyboard navigation of the user interface

Users can access z/OS user interfaces by using TSO/E or ISPF. Refer to *z/OS TSO/E Primer*, *z/OS TSO/E User's Guide*, and *z/OS ISPF User's Guide Volume 1* for information about accessing TSO/E and ISPF interfaces. These guides describe how to use TSO/E and ISPF, including the use of keyboard shortcuts or function keys (PF keys). Each guide includes the default settings for the PF keys and explains how to modify their functions.

Accessibility of this document

Information in the following formats of this document is accessible to visually impaired individuals who use a screen reader:

- PDF format when viewed with Adobe Acrobat Reader 5.0 or later
- BookManager format when viewed with IBM BookManager BookServer (except for syntax diagrams)

Syntax diagrams start with the word **Format** or the word **Fragments**. Each diagram is preceded by two images. For the first image, the screen reader will say "Read syntax diagram". The associated link leads to an accessible text diagram. When you return to the document at the second image, the screen reader will say "Skip visual syntax diagram" and has a link to skip around the visible diagram.

For BookManager users only: A screen reader might say the lines, symbols, and words in a diagram, but not in a meaningful way. For example, you might hear "question question dash dash MOVE dash dash plus dash dash literal-1 dash dash plus" for part of the MOVE statement. You can enter **Say Next Paragraph** to move quickly through syntax diagrams if your screen reader has that capability.

Notices

This information was developed for products and services offered in the U.S.A. IBM might not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Corporation
J46A/G4
555 Bailey Avenue
San Jose, CA 95141-1003
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with the local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Some states do not allow disclaimer of express or implied warranties in certain transactions; therefore, this statement might not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Copyright license

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or functions of these programs.

Programming interface information

This book is intended to help you debug application programs. This publication documents intended Programming Interfaces that allow you to write programs to obtain the services of Debug Tool.

Trademarks and service marks

The following terms, denoted by an asterisk (*) on the first occurrence in this publication, are trademarks or service marks of International Business Machines Corporation in the United States or other countries:

AIX	OS/390
CICS	Resource Link
COBOL/370	VisualAge
DB2	VSE/ESA
IBM	VTAM
IMS	WebSphere
Language Environment	z/OS
MVS	z/VM

Other company, product, and service names, which may be denoted by a double asterisk (**), may be trademarks or service marks of others.

LINUX is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, and Windows NT are registered trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a trademark of UNIX System Laboratories, licensed exclusively by X/Open Company, Ltd.

Bibliography

Debug Tool publications

Using CODE/370 with VS COBOL II and OS PL/I,
SC09-1862

Debug Tool for z/OS

*Debug Tool for z/OS Summary of Commands and
Built-in Functions,* SC18-9305

Debug Tool for z/OS Customization Guide,
SC18-9306

Program Directory for Debug Tool for z/OS,
GI10-8598

Debug Tool for z/OS Reference and Messages,
SC18-9304

Debug Tool for z/OS User's Guide, SC18-9302

Debug Tool Utilities and Advanced Functions for z/OS

Coverage Utility User's Guide and Messages,
SC18-9303

*Program Directory for Debug Tool Utilities and
Advanced Functions for z/OS,* GI10-8599

High level language publications

z/OS C and C++

Compiler and Run-Time Migration Guide,
GC09-4913

Curses, SA22-7820,

Language Reference, SC09-4815

Programming Guide, SC09-4765

Run-Time Library Reference, SA22-7821

User's Guide, SC09-4767

Enterprise COBOL for z/OS and OS/390

Migration Guide, GC27-1409

Customization, GC27-1410

Licensed Program Specifications, GC27-1411

Language Reference, SC27-1408

Programming Guide, SC27-1412

COBOL for OS/390 & VM

Compiler and Run-Time Migration Guide,
GC26-4764

Customization under OS/390, GC26-9045

Language Reference, SC26-9046

Programming Guide, SC26-9049

Enterprise PL/I for z/OS and OS/390

Diagnosis Guide, SC27-1459

Language Reference, SC27-1460

Licensed Program Specifications, GC27-1456

Messages and Codes, SC27-1461

Migration Guide, GC27-1458

Programming Guide, SC27-1457

VisualAge PL/I for OS/390

Compiler and Run-Time Migration Guide,
SC26-9474

Diagnosis Guide, SC26-9475

Language Reference, SC26-9476

Licensed Program Specifications, GC26-9471

Messages and Codes, SC26-9478

Programming Guide, SC26-9473

PL/I for MVS & VM

Compile-Time Messages and Codes, SC26-3229

*Compiler and Run-Time Migration
Guide* SC26-3118

Diagnosis Guide, SC26-3149

Installation and Customization under MVS,
SC26-3119

Language Reference, SC26-3114

Licensed Program Specifications, GC26-3116

Programming Guide, SC26-3113

Reference Summary, SX26-3821

Related publications

z/OS Language Environment

Concepts Guide, SA22-7567

Customization, SA22-7564

Debugging Guide, GA22-7560

Programming Guide, SA22-7561

Programming Reference, SA22-7562

Run-Time Migration Guide, GA22-7565

Vendor Interfaces, SA22-7568

*Writing Interlanguage Communication
Applications,* SA22-7563

z/OS

MVS JCL Reference, SA22-7597
MVS JCL User's Guide, SA22-7598
MVS System Commands, SA22-7627

OS/390

MVS JCL Reference, GC28-1757
MVS JCL User's Guide, GC28-1758
MVS System Commands, GC28-1781

TSO/E

Command Reference, SA22-7782
Programming Guide, SA22-7788
System Programming Command Reference,
SA22-7793
User's Guide, SA22-7794

CICS

Application Programming Guide, SC34-6231
Application Programming Primer, SC34-0674
Application Programming Reference, SC34-6232

IMS

*IMS Application Programming: Database
Manager*, SC26-8727
*IMS Application Programming: EXEC DLI
Commands for CICS & IMS*, SC26-8726
*IMS Application Programming: Transaction
Manager*, SC26-8729

DB2 UDB for OS/390 and z/OS

Administration Guide, SC26-9931
Application Programming and SQL Guide,
SC26-9933
Command Reference, SC26-9934
Data Sharing: Planning and Administration,
SC26-9935
Installation Guide, GC26-9936
Messages and Codes, GC26-9940
Reference for Remote DRDA Requesters and
Servers*, SC26-9942
Release Planning Guide, SC26-9943
SQL Reference, SC26-9944
Utility Guide and Reference, SC26-9945

Softcopy publications

Online publications are distributed on CD-ROMs and can be ordered through your IBM representative. *Debug Tool for z/OS User's Guide*, *Debug Tool for z/OS Customization Guide*, and *Debug Tool for z/OS Reference and Messages* are distributed on the following collection kit:

SK3T-4269

Online publications can also be downloaded from the IBM Web site. Visit the IBM Web site for each product to find online publications for that product.

Glossary

This glossary defines technical terms and abbreviations used in *Debug Tool for z/OS User's Guide* documentation. If you do not find the term you are looking for, refer to the *IBM Glossary of Computing Terms*, located at the IBM Terminology web site:

<http://www.ibm.com/ibm/terminology>

A

active block. The currently executing block that invokes Debug Tool or any of the blocks in the CALL chain that leads up to this one.

active server. A server that is being used by a remote debug session. Contrast with *inactive server*. See also *server*.

alias . An alternative name for a field used in some high-level programming languages.

animation. The execution of instructions one at a time with a delay between each so that any results of an instruction can be viewed.

attention interrupt. An I/O interrupt caused by a terminal or workstation user pressing an attention key, or its equivalent.

attention key. A function key on terminals or workstations that, when pressed, causes an I/O interrupt in the processing unit.

attribute. A characteristic or trait the user can specify.

Autosave. A choice allowing the user to automatically save work at regular intervals.

B

batch. Pertaining to a predefined series of actions performed with little or no interaction between the user and the system. Contrast with *interactive*.

batch job. A job submitted for batch processing. See *batch*. Contrast with *interactive*.

batch mode. An interface mode for use with the MFI Debug Tool that does not require input from the terminal. See *batch*.

block. In programming languages, a compound statement that coincides with the scope of at least one of the declarations contained within it.

breakpoint. A place in a program, usually specified by a command or a condition, where execution can be interrupted and control given to the user or to Debug Tool.

C

CADP. A CICS-supplied transaction used for managing debugging profiles from a 3270 terminal.

century window (COBOL). The 100-year interval in which COBOL assumes all windowed years lie. The start of the COBOL century window is defined by the COBOL YEARWINDOW compiler option.

command list. A grouping of commands that can be used to govern the startup of Debug Tool, the actions of Debug Tool at breakpoints, and various other debugging actions.

compile. To translate a program written in a high level language into a machine-language program.

compile unit. A sequence of HLL statements that make a portion of a program complete enough to compile correctly. Each HLL product has different rules for what comprises a compile unit.

compiler. A program that translates instructions written in a high level programming language into machine language.

condition. Any synchronous event that might need to be brought to the attention of an executing program or the language routines supporting that program. Conditions fall into two major categories: conditions detected by the hardware or operating system, which result in an interrupt; and conditions defined by the programming language and detected by language-specific generated code or language library code. An example of a hardware condition is division by zero. An example of a software condition is end-of-file. See also *exception*.

conversational. A transaction type that accepts input from the user, performs a task, then returns to get more input from the user.

currently qualified. See *qualification*.

D

data type. A characteristic that determines the kind of value that a field can assume.

data set. The major unit of data storage and retrieval, consisting of a collection of data in one of several prescribed arrangements and described by control information to which the system has access.

date field. A COBOL data item that can be any of the following:

- A data item whose data description entry includes a DATE FORMAT clause.
- A value returned by one of the following intrinsic functions:
 - DATE-OF-INTEGER
 - DATE-TO-YYYYMMDD
 - DATEVAL
 - DAY-OF-INTEGER
 - DAY-TO-YYYYDDD
 - YEAR-TO-YYYY
 - YEARWINDOW
- The conceptual data items DATE and DAY in the ACCEPT FROM DATE and ACCEPT FROM DAY statements, respectively.
- The result of certain arithmetic operations.

The term date field refers to both *expanded date field* and *windowed date field*. See also *nodate*.

date processing statement. A COBOL statement that references a date field, or an EVALUATE or SEARCH statement WHEN phrase that references a date field.

DBCS. See *double-byte character set*.

debug. To detect, diagnose, and eliminate errors in programs.

DTCN. Debug Tool Control utility, a CICS transaction that enables the user to identify which CICS programs to debug.

Debug Tool procedure. A sequence of Debug Tool commands delimited by a PROCEDURE and a corresponding END command.

Debug Tool variable. A predefined variable that provides information about the user's program that the user can use during a session. All of the Debug Tool variables begin with %, for example, %BLOCK or %CU.

debugging profile. Data that specifies a set of application programs which are to be debugged together.

default. A value assumed for an omitted operand in a command. Contrast with *initial setting*.

double-byte character set (DBCS). A set of characters in which each character is represented by two bytes. Languages such as Japanese, which contain more symbols than can be represented by 256 code points, require double-byte character sets. Because each character requires two bytes, the typing, displaying,

and printing of DBCS characters requires hardware and programs that support these characters.

dynamic. In programming languages, pertaining to properties that can only be established during the execution of a program; for example, the length of a variable-length data object is dynamic. Contrast with *static*.

dynamic link library (DLL). A file containing executable code and data bound to a program at load time or run time. The code and data in a dynamic link library can be shared by several applications simultaneously. See also *load module*.

E

enclave. An independent collection of routines in Language Environment, one of which is designated as the MAIN program. The enclave contains at least one thread and is roughly analogous to a program or routine. See also *thread*.

entry point. The address or label of the first instruction executed on entering a computer program, routine, or subroutine. A computer program can have a number of different entry points, each perhaps corresponding to a different function or purpose.

exception. An abnormal situation in the execution of a program that typically results in an alteration of its normal flow. See also *condition*.

execute. To cause a program, utility, or other machine function to carry out the instructions contained within. See also *run*.

execution time. See *run time*.

execution-time environment. See *run-time environment*.

expanded date field. A COBOL date field containing an expanded (four-digit) year. See also *date field* and *expanded year*.

expanded year. In COBOL, four digits representing a year, including the century (for example, 1998). Appears in expanded date fields. Compare with *windowed year*.

expression. A group of constants or variables separated by operators that yields a single value. An expression can be arithmetic, relational, logical, or a character string.

F

file. A named set of records stored or processed as a unit. An element included in a container: for example, an MVS member or a partitioned data set. See also *data set*.

frequency count. A count of the number of times statements in the currently qualified program unit have been run.

full-screen mode. An interface mode for use with a nonprogrammable terminal that displays a variety of information about the program you are debugging.

H

high level language (HLL). A programming language such as C, COBOL, or PL/I.

HLL. See *high level language*.

hook. An instruction inserted into a program by a compiler when you specify the TEST compile option. Using a hook, you can set breakpoints to instruct Debug Tool to gain control of the program at selected points during its execution.

I

inactive block. A block that is not currently executing, or is not in the CALL chain leading to the active block. See also *active block*, *block*.

initial setting. A value in effect when the user's Debug Tool session begins. Contrast with *default*.

interactive. Pertaining to a program or system that alternately accepts input and then responds. An interactive system is conversational; that is, a continuous dialog exists between the user and the system. Contrast with *batch*.

I/O . Input/output.

L

Language Environment. An IBM software product that provides a common run-time environment and common run-time services for IBM high level language compilers.

library routine. A routine maintained in a program library.

line mode. An interface mode for use with a nonprogrammable terminal that uses a single command line to accept Debug Tool commands.

line wrap. The function that automatically moves the display of a character string (separated from the rest of a line by a blank) to a new line if it would otherwise overrun the right margin setting.

link-edit. To create a loadable computer program using a linkage editor.

linkage editor. A program that resolves cross-references between separately compiled object modules and then assigns final addresses to create a single relocatable load module.

listing. A printout that lists the source language statements of a program with all preprocessor statements, includes, and macros expanded.

load module. A program in a form suitable for loading into main storage for execution. In this document this term is also used to refer to a Dynamic Load Library (DLL).

M

minor node. In VTAM, a uniquely defined resource within a major node.

multitasking. A mode of operation that provides for concurrent performance, or interleaved execution of two or more tasks.

N

nonconversational. A transaction type that accepts input, performs a task, and then ends.

nondate. A COBOL data item that can be any of the following:

- A data item whose date description entry does not include the DATE FORMAT clause
- A literal
- A reference modification of a date field
- The result of certain arithmetic operations that may include date field operands; for example, the difference between two compatible date fields.

The value of a nondate may or may not represent a date.

O

Options. A choice that lets the user customize objects or parts of objects in an application.

P

panel. In Debug Tool, an area of the screen used to display a specific type of information.

parameter. Data passed between programs or procedures.

partitioned data set (PDS). A data set in direct access storage that is divided into partitions, called members, each of which can contain a program, part of a program, or data.

path point. A point in the program where control is about to be transferred to another location or a point in the program where control has just been given.

PDS. See *partitioned data set*.

prefix area. The eight columns to the left of the program source or listing containing line numbers. Statement breakpoints can be set in the prefix area.

primary entry point. See *entry point*.

procedure. In a programming language, a block, with or without formal parameters, whose execution is invoked by means of a procedure call. A set of related control statements. For example, an MVS CLIST.

process. The highest level of the Language Environment program management model. It is a collection of resources, both program code and data, and consists of at least one enclave.

Profile. A choice that allows the user to change some characteristics of the working environment, such as the pace of statement execution in the Debug Tool.

program. A sequence of instructions suitable for processing by a computer. Processing can include the use of an assembler, a compiler, an interpreter, or a translator to prepare the program for execution, as well as to execute it.

program unit. See *compile unit*.

program variable. A predefined variable that exists when Debug Tool was invoked.

pseudo-conversational transaction. The result of a technique in CICS called pseudo-conversational processing in which a series of nonconversational transactions gives the appearance (to the user) of a single conversational transaction. See *conversational* and *nonconversational*.

Q

qualification. A method used to specify to what procedure or load module a particular variable name, function name, label, or statement id belongs. The SET QUALIFY command changes the current implicit qualification.

R

record. A group of related data, words, or fields treated as a unit, such as one name, address, and telephone number.

record format. The definition of how data is structured in the records contained in a file. The definition includes record name, field names, and field

descriptions, such as length and data type. The record formats used in a file are contained in the file description.

reference. In programming languages, a language construct designating a declared language object. A subset of an expression that resolves to an area of storage; that is, a possible target of an assignment statement. It can be any of the following: a variable, an array or array element, or a structure or structure element. Any of the above can be pointer-qualified where applicable.

run. To cause a program, utility, or other machine function to execute. An action that causes a program to begin execution and continue until a run-time exception occurs. If a run-time exception occurs, the user can use Debug Tool to analyze the problem. A choice the user can make to start or resume regular execution of a program.

run time. Any instant when a program is being executed.

run-time environment. A set of resources that are used to support the execution of a program.

run unit. A group of one or more object programs that are run together.

S

SBCS. See *single-byte character set*.

semantic error. An error in the implementation of a program's specifications. The semantics of a program refer to the meaning of a program. Unlike syntax errors, semantic errors (since they are deviations from a program's specifications) can be detected only at run time. Contrast with *syntax error*.

sequence number. A number that identifies the records within an MVS file.

session variable. A variable the user declares during the Debug Tool session by using Declarations.

single-byte character set (SBCS). A character set in which each character is represented by a one-byte code.

Single Point of Control. The control interface that sends commands to one or more members of an IMSplex and receives command responses.

source. The HLL statements in a file that make up a program.

Source window. A Debug Tool window that contains a display of either the source code or the listing of the program being debugged.

SPOC. See "Single Point of Control."

static. In programming languages, pertaining to properties that can be established before execution of a program; for example, the length of a fixed-length variable is static. Contrast with *dynamic*.

step. One statement in a computer routine. To cause a computer to execute one or more statements. A choice the user can make to execute one or more statements in the application being debugged.

storage. A unit into which recorded text can be entered, in which it can be retained, and from which it can be retrieved. The action of placing data into a storage device. A storage device.

subroutine. A sequenced set of instructions or statements that can be used in one or more computer programs at one or more points in a computer program.

suffix area. A variable-sized column to the right of the program source or listing statements, containing frequency counts for the first statement or verb on each line. Debug Tool optionally displays the suffix area in the Source window. See also *prefix area*.

syntactic analysis. An analysis of a program done by a compiler to determine the structure of the program and the construction of its source statements to determine whether it is valid for a given programming language. See also *syntax checker*, *syntax error*.

syntax. The rules governing the structure of a programming language and the construction of a statement in a programming language.

syntax error. Any deviation from the grammar (rules) of a given programming language appearing when a compiler performs a syntactic analysis of a source program. See also *syntactic analysis*.

T

session variable. See *session variable*.

thread. The basic line of execution within the Language Environment program model. It is dispatched with its own instruction counter and registers by the system. Threads can execute, concurrently with other threads. The thread is where actual code resides. It is synonymous with a CICS transaction or task. See also *enclave*.

thread id. A small positive number assigned by Debug Tool to a Language Environment task.

token. A character string in a specific format that has some defined significance in a programming language.

trigraph. A group of three characters which, taken together, are equivalent to a single special character. For example, `??)` and `??(` are equivalent to the left (`<`) and right (`>`) brackets.

U

utility. A computer program in general support of computer processes; for example, a diagnostic program, a trace program, or a sort program.

V

variable. A name used to represent a data item whose value can be changed while the program is running.

VTAM. See “Virtual Telecommunications Access Method.”

Virtual Telecommunications Access Method (VTAM). (1) IBM software that controls communication and the flow of data in an SNA network by providing the SNA application programming interfaces and SNA networking functions. An SNA network includes subarea networking, Advanced Peer-to-Peer Networking (APPN), and High-Performance Routing (HPR). Beginning with Release 5 of the OS/390 operating system, the VTAM for MVS/ESA function was included in Communications Server for OS/390; this function is called Communications Server for OS/390 - SNA Services. (2) An access method commonly used by MVS to communicate with terminals and other communications devices.

W

windowed date field. A COBOL date field containing a windowed (two-digit) year. See also *date field* and *windowed year*.

windowed year. In COBOL, two digits representing a year within a century window (for example, 98). Appears in windowed date fields. See also *century window (COBOL)*.

Compare with *expanded year*.

word wrap. See *line wrap*.

Index

Special characters

- `__ctest()` function 86
- `%CONDITION` variable
 - for PL/I 229
- `%PATHCODE` variable
 - for C and C++ 240
 - for PL/I 228
 - values for COBOL 214
- `#pragma` 40
 - specifying TEST compiler option 40
 - specifying TEST run-time option with 78

A

- ABEND 4038 312
- abnormal end of application, setting breakpoint at 303
- accessing PL/I program variables 231
- ALLOCATE command
 - managing file allocations 131
- ambiguous names 131
- applications 287
- assembler
 - debugging a program in full-screen mode
 - displaying variable or storage 190
 - finding storage overwrite errors 192
 - getting a function traceback 191
 - modifying variables or storage 190
 - multiple CUs in single assembly 189
 - stopping at assembler routine call 190
 - stopping when condition is true 191
 - restrictions 265
 - while debugging MAIN program 266
 - with STORAGE run-time option 266
 - sample program for debugging 185
 - self-modifying code, restrictions 266, 271
- assembler program
 - loading debug information 261
 - locating EQALANGX 261
 - making assembler CUs known to Debug Tool 262
- assembler programs
 - assembling, requirements 46
 - requirements for debugging 45
 - using Debug Tool Utilities to assemble and create 47
- assembler, definition of xv
- assembling your program, requirements for 46
- assigning values to variables 211, 239

- AT commands
 - AT CALL
 - breakpoints, for C++ 256
 - AT ENTRY
 - breakpoints, for C++ 255
 - AT EXIT
 - breakpoints, for C++ 255
- attention interrupt
 - effect of during Dynamic Debug 134
 - effect of during interactive sessions 134
 - how to initiate 134
 - required Language Environment run-time options 134
- attributes of variables 306

B

- batch mode 74
 - debugging CICS programs in 284
 - debugging DB2 programs in 277
 - debugging IMS programs in 282
 - description of 5
 - for non-Language Environment programs 92
 - starting Debug Tool in 91
 - using Debug Tool in 333
- binding DB2 programs 51
- blanks, significance of 206
- blocks and block identifiers
 - using, for C 250
- breakpoint
 - clearing 16
 - implicit 74
 - using DISABLE and ENABLE 16
- breakpoints
 - before calling a NULL function
 - in C 172
 - in C++ 183
 - before calling an invalid program, in COBOL 146
 - before calling an undefined program, in PL/I 162
 - halting if a condition is true
 - in C 167
 - in C++ 178
 - in COBOL 142
 - in PL/I 159
 - halting when certain COBOL routines are called 140
 - halting when certain functions are called
 - in C 166
 - in C++ 177
 - in PL/I 158
- recording, using SET AUTOMONITOR 124
- setting a line 124
- setting, in C++ 255

C

- C
 - debugging a program in full-screen mode
 - calling a C function from Debug Tool 168
 - capturing output to stdout 168
 - debugging a DLL 169
 - displaying raw storage 169
 - displaying strings 169
 - finding storage overwrite errors 170
 - finding uninitialized storage errors 171
 - getting a function traceback 169
 - halting on line if condition true 167
 - halting when certain functions are called 166
 - modifying value of variable 166
 - setting breakpoint to halt 172
 - tracing run-time path for code compiled with TEST 170
 - when not all parts compiled with TEST 168
 - sample program for debugging 163
 - syntax of TEST compiler option 338
- C and C++
 - AT ENTRY/EXIT breakpoints 255
 - blocks and block identifiers 250
 - commands
 - summary 237
 - equivalents for Language Environment conditions 244
 - function calls for 242
 - notes on using 204
 - reserved keywords 243
- C++ 137
 - AT CALL breakpoints 256
 - debugging a program in full-screen mode
 - calling a C++ function from Debug Tool 180
 - capturing output to stdout 180
 - debugging a DLL 180
 - displaying raw storage 180
 - displaying strings 180
 - finding storage overwrite errors 182
 - finding uninitialized storage errors 182
 - getting a function traceback 181
 - halting on a line if condition true 178
 - modifying value of variable 177
 - setting a breakpoint to halt 177, 183
 - tracing the run-time path 181
 - viewing and modifying data members 179

C++ (*continued*)

- debugging a program in full-screen mode (*continued*)
 - when not all parts compiled with TEST 179
- examining objects 257
- overloaded operator 255
- sample program for debugging 137, 173
- setting breakpoints 255
- stepping through C++ programs 255
- syntax of TEST compiler option 339
- template in C++ 255

CADP

- overview 98

CAF (call access facility), using to start DB2 program 278

call access facility (CAF), using to start DB2 program 278

capturing output to stdout

- in C 168
- in C++ 180

CEEBXITA

- See* EQADCCXT

CEETEST

- description 80
- examples, for C 81
- examples, for COBOL 83
- examples, for PL/I 84
- Starting Debug Tool with 79
- using 282

CEEUOPT run-time options module 50

CEEUOPT to start Debug Tool under CICS, using 98

changing the value of a variable, introduction to 16

changing window layout in the session panel 194

character set 203

characters, searching 120

CICS

- debug modes under 284
- pseudo-conversational program 284
- requirements for using Debug Tool in 283
- restoring breakpoints 285
- restrictions for debugging 285
- saving breakpoints 285
- starting Debug Tool under 96
- starting the log file 285

CICS, starting Debug Tool under 95

closing automonitor section of Monitor window 129

closing Debug Tool session panel windows 195

COBOL

- command format 210
- Convert and Compile option 27
- debugging a program in full-screen mode
 - capturing I/O to system console 143
 - displaying raw storage 144
 - finding storage overwrite errors 146
 - generating a run-time paragraph trace 145

COBOL (*continued*)

- debugging a program in full-screen mode (*continued*)
 - modifying the value of a variable 141
 - setting a breakpoint to halt 140
 - setting breakpoint to halt 146
 - stopping on line if condition true 142
 - tracing the run-time path 144
 - when not all parts compiled with TEST 143
- debugging COBOL classes 219
- debugging VS COBOL II programs 220
 - finding listing 220
- FACTORY 219
- list of compilers that support SEPARATE 209
- listing files 209
- note on using H constant 207
- notes on using 204
- OBJECT 220
- optimized programs, debugging 291
- paragraph trace, generating a COBOL run-time 145
- preparing, programs to debug 25
- reserved keywords 211
- restrictions on accessing, data 127
- run-time options 77
- syntax of TEST compiler option 340
- variables, using with Debug Tool 211

COBOL listing, data set 321

coexistence of Debug Tool with other debuggers 308

coexistence with unsupported HLL modules 308

colors

- changing in session panel 196

command

- syntax diagrams xvi

command format

- for COBOL 210

command line, Debug Tool 114

command sequencing, full-screen mode 115

commands

- abbreviating 204
- DTSU, using to debug DB2 program 277
- for C and C++, Debug Tool subset 237
- for PL/I, Debug Tool subset 227
- getting online help for 207
- interpretive subset
 - description 300
- list of Debug Tool Advanced Functions 7
- multiline 205
- PLAYBACK 17
- prefix, using in Debug Tool 116
- truncating 204
- TSO, using to debug DB2 program 277

commands (system), entering in Debug Tool 116

commands file 74, 323

commands file (*continued*)

- example of specifying 91
- using log file as 122
- using session log as 75

commands, Debug Tool

- COBOL compiler options in effect 210
- entering on the session panel 114
- entering using program function keys 117
- order of processing 115
- retrieving with RETRIEVE command 118
- that resemble COBOL statements 209

comments, inserting into command stream 206

common_parameters, when to use 9

compile unit 115

- general description 301
- name area, Debug Tool 115
- qualification of, for C and C++ 252

compiling

- a C program on an HFS file system 39
- a C++ program on an HFS file system 42
- an OS/VS COBOL program 27
- considerations 21
- DB2 programs for debugging 50
- Enterprise PL/I program on HFS file system 34
- IMS programs 63
- OS PL/I 34
- PL/I for MVS & VM program 34
- programs, introduction to 11

condition

- handling of 229, 304
- Language Environment, C and C++ equivalents 244

considerations

- before compiling and debugging 21
- when using the TEST run-time option 73

constants

- Debug Tool interpretation of
 - HLL 300
- entering 207
- HLL 300
- PL/I 232
- using in expressions, for COBOL 216

constructor, stepping through 255

continuation character 116

- for COBOL 210
- using in full-screen 205

continuing lines 205

continuous display

- See* monitoring

Convert and Compile option 27

copying

- JCL into a setup file using DTSU 70

creating

- setup file using Debug Tool Utilities 69

CURSOR command

- using 119

cursor commands

- CLOSE 195

cursor commands (*continued*)

- CURSOR 119
- FIND 120
- OPEN 195
- SCROLL 109, 119
- SIZE 195
- using in Debug Tool 117
- WINDOW ZOOM 196

customizing

- PF keys 193
- Profile panel 73
- profile settings 197
- session settings 193

D

DATA parameter

- restrictions on accessing COBOL data 127

data sets

- COBOL listing 321
- PL/I listing 322
- PL/I source 321
- separate debug file 322
- specifying 122
- used by Debug Tool 321

DB2

- compiling programs for debugging 50
- DB2 programs for debugging 49
- linking programs 50
- using Debug Tool with 277

DB2 stored procedures

- preparing for debugging 53
- starting Debug Tool from 103
- using Debug Tool with 279

DBCS

- using with C 204
- using with COBOL 213
- using with Debug Tool commands 203

ddname

- creating a log file in Debug Tool 122

debug session

- ending 134
- recording 112
- starting 101
- starting your program 101

Debug Tool

- C and C++ commands, interpretive subset 237
- COBOL commands, interpretive subset 209
- commands, subset 300
- condition handling 304
- data sets 321
- evaluation of HLL expressions 299
- exception handling, for C and C++ and PL/I 305
- interfaces 4
- interpretation of HLL variables 300
- list of supported compilers 3
- list of supported subsystems 3
- multilanguage programs, using PL/I commands, interpretive subset 227
- starting at different points 74

Debug Tool (*continued*)

- starting under CICS 95, 96
- starting under IMS 282
- starting under MVS in TSO 89
- starting your program with 101
- starting, by using Debug Tool Utilities 69
- stopping, session 18
- terminology xv
- using in batch mode 333
- using in remote debug mode 335

Debug Tool Advanced Functions, list of 7

Debug Tool Setup Utility 69

Debug Tool Utilities

- creating and managing setup files 8
- creating private message region for IMS program 64
- creating setup file for IMS program 64
- how to use, to link-edit 48
- overview of code coverage tasks 9
- overview of IMS program preparation tasks 9
- overview of program preparation tasks 8
- preparing an IMS program by using 63
- specifying TEST run-time options for IMS program 64
- starting your program 72
- using to assemble and create 47

Debug Tool Utilities and Advanced

Functions

- introduction 7
- tasks it helps you with 7

Debug Tool Utilities, list of 7

debuggers, coexistence with other 308

debugging

- CICS programs 283
- COBOL classes 219
- considerations 21
- DB2 programs 277
- DB2 stored procedures 279
- DLL

- in C 169

- in C++ 180

- IMS programs 281

- in full-screen mode 107

- ISPF applications 287

- multithreading programs 309

- non-Language Environment

- programs 295

- optimized programs, prevention 26

- UNIX System Services programs 293

declaring session variables

- for C 240

- for COBOL 215

deferring an LDD command 152

DESCRIBE ALLOCATIONS command

- managing file allocations 131

DESCRIBE command

- using 252

destructor, stepping through 255

diagnostics, expression, for C and C++ 245

disassembly

- changing program in disassembly view 272
- differences between SET ASSEMBLER and SET DISASSEMBLY 261, 269
- displaying registers 272
- displaying storage 272
- modifying registers 272
- modifying storage 272
- performing single-step operations 271
- restrictions on what you can debug 272
- self-modifying code, restrictions 266, 271
- setting breakpoints 271
- what you can do is disassembly view 269

disassembly view, description of 270

disassembly view, how to start 270

displaying

- environment information 252

- halted location 121

- lines at top of window, Debug Tool 120

- raw storage

- in C 169

- in C++ 180

- in COBOL 144

- in PL/I 160

- source or listing file in full-screen mode 113

- strings

- in C 169

- in C++ 180

- value of variable one time 128

- values of COBOL variables 213

- variable value 127

displaying the value of a variable,

- introduction to 15

displaying variable value

- See* LIST commands

DLL debugging

- in C 169

- in C++ 180

documents, licensed xi

DOWN, SCROLL command 119

DTCN

- creating a profile 56

- data entry verification 59

- description 96

- modifying Language Environment

- options 59

- overview 97

- preparing to start Debug Tool 55

- using repository profile items 97

DTSU

- See* Debug Tool Setup Utility

dual terminal mode (CICS) 284

Dynamic Debug

- activating 22, 23

- attention interrupts, support for 134

E

- editing
 - setup file using Debug Tool Setup Utility 69
- elements, unsupported, for PL/I 234
- enclave
 - multiple, debugging interlanguage communication application in 317
 - starting 311
- ending
 - debug session 134
 - Debug Tool within multiple enclaves 312
- entering
 - commands on session panel 114
 - file allocation statements into setup file 70
 - program parameters into setup file 70
 - run-time option into setup file 70
- entering multiline commands without continuation 206
- entering PL/I statements, freeform 230
- Enterprise PL/I, definition of xv
- EQADCCXT 55, 56
- EQADCCXT user exit 75, 97
- EQADTCN2 60
- EQALANGX file
 - how to create 46
- EQALANGX files, how Debug Tool locates 325, 326
- EQASTART, entering command 9
- EQUATE, SET command
 - description 194
- error numbers in Log window 133
- evaluating expressions
 - COBOL 215
 - HLL 299
- evaluation of expressions
 - C and C++ 245
- examining C++ objects 257
- examples
 - assembler
 - sample program for debugging 185
- C
 - sample program for debugging 163
- C and C++
 - assigning values to variables 239
 - blocks and block identifiers 251
 - expression evaluation 242
 - monitoring and modifying registers and storage 258
 - referencing variables and setting breakpoints 251
 - scope and visibility of objects 251
- C++
 - displaying attributes 257
 - sample program for debugging 137, 173
 - setting breakpoints 256
- CEDF procedure 100
- CEETEST calls, for PL/I 84
- CEETEST function calls, for C 81
- CEETEST function calls, for COBOL 83

- examples (*continued*)
 - changing point of view, general 303
- COBOL
 - %HEX function 217
 - %STORAGE function 217
 - assigning values to COBOL variables 212
 - changing point of view 219
 - displaying results of expression evaluation 216
 - displaying values of COBOL variables 213
 - qualifying variables 218
 - using constants in expressions 217
- declaring variables, for COBOL 215
- displaying program variables 239
- modifying setup files by using Debug Tool Utilities 327
- PL/I
 - in PL/I 158
 - sample program for debugging 155
- PLITEST calls for PL/I 85
- preparing programs by using Debug Tool Utilities 327
- remote debug mode 77
- specifying TEST run-time option with #pragma 78
- TEST run-time option 76
- using #pragma for TEST compiler option 40
- using constants 207
- using continuation characters 205
- using qualification 252

exception handling for C and C++ and PL/I 305

EXEC CICS RETURN under CICS 284

executing

- See* running

expressions

- diagnostics, for C and C++ 245
- displaying values, for C and C++ 238
- displaying values, for COBOL 216
- evaluation for C and C++ 241, 245
- evaluation for COBOL 215
- evaluation of HLL 299
- evaluation, operators and operands for C 243
- for PL/I 232
- using constants in, for COBOL 216

F

- FIND command
 - using with windows 120
- finding
 - characters or strings 120
 - renamed source, listing or separate debug file 133
 - storage overwrite errors
 - in assembler 192
 - in C 170
 - in C++ 182
 - in COBOL 146

- finding (*continued*)
 - storage overwrite errors (*continued*)
 - in PL/I 162
 - uninitialized storage errors
 - in C 171
 - in C++ 182
- FREE command
 - managing file allocations 131
- freeform input, PL/I statements 230
- full-screen mode
 - continuation character, using in 205
 - CURSOR 117
 - CURSOR command 119
 - debugging in 107
 - description of 4
 - introduction to 11
 - PANEL COLORS 196
 - PANEL LAYOUT 194
 - PANEL PROFILE 197
 - screen 12
 - SCROLL 119
 - WINDOW CLOSE 195
 - WINDOW OPEN 195
 - WINDOW SIZE 195
 - WINDOW ZOOM 196
- full-screen mode through a VTAM terminal
 - description of 4
 - starting a debugging session 103
- function calls, for C and C++ 242
- function, calling C and C++ from Debug Tool
 - C 168
 - C++ 180
- function, unsupported for PL/I 234
- functions
 - PL/I 232
- functions, Debug Tool
 - %HEX
 - using with COBOL 217
 - %STORAGE
 - using with COBOL 217

G

- global data 258
- global preferences file 323
- global scope operator 258

H

- H constant (COBOL) 207
- halted location, displaying 121
- header fields, Debug Tool session panel 108
- help, online
 - for command syntax 207
- hexadecimal format, displaying values in 129
- hexadecimal format, displaying variable values in 128
- hexadecimal format, how to display value of variable 129
- hexadecimal format, how to monitor value of variable 130

- hexadecimal format, monitoring values in 130
- HFS, compiling a C program on 39
- HFS, compiling a C++ program on 42
- HFS, compiling Enterprise PL/I program on 34
- highlighting, changing in Debug Tool session panel 196
- history, Debug Tool command 118
 - retrieving previous commands 118
- HOOK C++ TEST suboption 340
- hooks
 - compiling with 21
 - compiling with, C 37
 - compiling with, COBOL 26
 - compiling with, PL/I 33
 - compiling without, COBOL 21
 - removing from application 289, 290
 - removing, implications of 22
 - rules for placing 39, 42
- I**
- I/O, COBOL
 - capturing to system console 143
- improving Debug Tool performance 289
- IMS
 - preparing
 - by using Debug Tool Utilities 63
 - programs, compiling 63
 - programs, debugging
 - interactively 281
 - programs, linking 65
 - using Debug Tool with 281
- information, displaying
 - environmental 252
- input areas, order of processing, Debug Tool 115
- INSPLOG
 - creating the log file 122
 - DD name to store log file 323
 - example of using 90
- INSPSAFE
 - default DD name to store preference settings 323
 - example of using 90
 - using to save profile settings 199
 - using to save session panel colors 197
- interfaces
 - batch mode 5
 - full-screen mode 4
 - full-screen mode through a VTAM terminal 4
 - remote debug mode 5
- interfaces, description of 4
- interLanguage communication (ILC)
 - application, debugging 317
- interlanguage programs, using with Debug Tool 305
- interpretive subset
 - general description 300
 - of C and C++ commands 237
 - of COBOL statements 209
 - of PL/I commands 227
- INTERRUPT, Language Environment
 - run-time option 134

- invoking
 - See starting
- ISPF
 - starting 116
- J**
- JCL to create EQALANGX file 46
- K**
- keywords, abbreviating 204
- L**
- Language Environment
 - conditions, C and C++
 - equivalents 244
 - EQADCCXT user exit 75, 97
 - run-time options, precedence 75
- LDD command, example 261
- LEFT, SCROLL command 119
- licensed documents xi
- line breakpoint, setting 124
- line continuation
 - for C 205
 - for COBOL 206
- link-edit assembler program
 - how to, by using Debug Tool Utilities 48
- linking
 - DB2 programs 50
 - EQADCCXT 55
 - IMS programs 65
- LIST %HEX command 129
- LIST command
 - use to display value of variable one time 128
- LIST commands
 - LIST STORAGE
 - using with PL/I 230
- listing
 - file, finding renamed 133
 - files, for COBOL 209
 - find, OS PL/I 234
 - find, VS COBOL II 220
- listing files, how Debug Tool locates 325
- literal constants, entering 207
- log file 122, 323
 - creating 122
 - default names 122
 - using 122
 - using as a commands file 122
- Log window
 - description 112
 - error numbers in 133
 - retrieving lines from 118
- log, session 75
- LookAt message retrieval tool xii
- low-level debugging 258

- M**
- managing file allocations 131
- message retrieval tool, LookAt xii

- modifying
 - value of variable 130
 - value of variable by typing over 130
- modifying value of a C variable 166
- MONITOR command
 - viewing output from, Debug Tool 111
- MONITOR LIST command, using to monitor variables 128
- Monitor window
 - description 111
 - opening and closing 131, 195
- monitoring 128
- monitoring storage in C++ 258
- more than one language, debugging programs with 305
- moving around windows in Debug Tool 119
- moving the cursor, Debug Tool 119
- multilanguage programs, using with Debug Tool 305
- multiline commands
 - continuation character, using in 205
 - without continuation character 206
- multiple enclaves
 - ending Debug Tool 312
 - interlanguage communication
 - application, debugging 317
 - starting 311
- multithreading 309
 - restrictions 309
- MVS
 - starting Debug Tool using TEST
 - run-time option 101
- MVS POSIX programs, debugging 293
- MVS, starting Debug Tool under 89

- N**
- navigating session panel windows 119
- non-Language Environment programs
 - debugging 295
 - starting Debug Tool 92
- NOTEST suboption of TEST run-time option 74

- O**
- objects
 - C and C++, scope of 248
- opening Debug Tool session panel windows 195
- operators and operands for C 243
- optimized programs, debugging
 - COBOL 291
- options module, CEEUOPT run-time 50
- OS PL/I programs, debugging 234
- OS PL/I, finding list for 234
- output
 - C, capturing to stdout 168
 - C++, capturing to stdout 180
- overloaded operator 255
- overwrite errors, finding storage
 - in assembler 192
 - in C 170
 - in C++ 182

overwrite errors, finding storage
(continued)
in COBOL 146
in PL/I 162

P

panel
header fields, session 108
Profile 197
PANEL command (full-screen mode)
changing session panel colors and
highlighting 196
paragraph trace, generating a COBOL
run-time 145
performance, improving Debug Tool 289
PF keys
defining 193
using 117
PF4 key, using 128
PL/I 155
built-in functions 232
condition handling 229
constants 232
debugging a program in full-screen
mode
displaying raw storage 160
finding storage overwrite
errors 162
getting a function traceback 160
halting on line if condition is
true 159
modifying value of variable 158
setting a breakpoint to halt 158
setting breakpoint to halt 162
tracing run-time path for code
compiled with TEST 161
when not all parts compiled with
TEST 159
debugging OS PL/I programs 234
finding listing 234
expressions 232
notes on using 204
preparing a program for
debugging 33
run-time options 77
sample program for debugging 155
session variables 230
statements 227
structures, accessing 231
syntax of TEST compiler option 343
PL/I listing, data set 322
PL/I source, data set 321
PLAYBACK commands
introduction to 17
PLAYBACK BACKWARD
using 126
PLAYBACK DISABLE
using 126
PLAYBACK ENABLE
using 125
PLAYBACK FORWARD
using 126
PLAYBACK START
using 126
PLAYBACK STOP
using 126

PLITEST 85
point of view, changing
description 303
for C and C++ 253
with COBOL 219
positioning lines at top of windows 120
precompiling DB2 programs 49
preference file 59, 73
preferences file 322
customizing with 199
prefix area
Debug Tool 115
prefix commands
prefix area on session panel 115
using in Debug Tool 116
prepare an assembler program, steps
to 45
preparing
a PL/I program for debugging 33
COBOL programs for debugging 25
DB2 stored procedures 53
to replay recorded statements using
PLAYBACK START command 126
previous commands, retrieving 118
profile settings, changing in Debug
Tool 197
program
CICS, debugging 283
compiling an IMS 63
DB2, debugging 277
hook
compiling with, C 37
compiling with, COBOL 26
compiling with, PL/I 33
removing 289, 290
rules for placing 39, 42
IMS, debugging 281
linking an IMS 65
multithreading, debugging 309
preparation
considerations, size and
performance 289, 290
TEST compiler option, for C 37
TEST compiler option, for C++ 41
TEST compiler option, for
COBOL 25
TEST compiler option, for
PL/I 33
TEST compiler option, for VS
COBOL II 26
reducing size 289
source, displaying with Debug
Tool 110
starting for a debug session 95
stepping through 124
UNIX System Services,
debugging 293
variables
accessing for C and C++ 238
variables, accessing for COBOL 211
pseudo-conversational program, saving
settings 284
PX constant (PL/I) 207

Q

qualification
description, for C and C++ 252
general description 301
qualifying variables
with COBOL 217

R

recording
breakpoints using SET
AUTOMONITOR 124
number of times each source line
runs 123
restrictions on, statements 127
session with the log file 122
statements, introduction to 17
statements, using PLAYBACK
ENABLE command 125
stopping, using PLAYBACK DISABLE
command 126
recording a debug session 112
referencing variables, implications of 22
remote debug mode
description of 5
examples of 77
using Debug Tool in 335
removing statement and symbol
tables 290
replaying
statements, introduction to 17
replaying recorded statements 126
replaying statements
changing direction of 126
direction of 126
restrictions on 127
stopping using PLAYBACK STOP
command 126
using PLAYBACK commands 124
using PLAYBACK START
command 126
requirements
for debugging CICS programs 283
reserved keywords
for C 243
for COBOL 211
RESIDENT compiler option 27
resources to collect 24
restrictions 210
accessing COBOL data, for 127
arithmetic expressions, for
COBOL 215
debugging OS PL/I programs 234
debugging VS COBOL II
programs 220
expression evaluation, for
COBOL 215
location of source on HFS 34, 39, 42
modifying variables in Monitor
window 130
recording and replaying statements,
for 127
string constants in COBOL 216
when debugging multilanguage
applications 309
when debugging under CICS 285

- restrictions (*continued*)
 - when using a continuation character 210
 - when using TEST 338, 340
 - while debugging assembler programs 265
- RETRIEVE command
 - using 118
- retrieving commands
 - with RETRIEVE command 118
- retrieving lines from Log or Source windows 118
- RIGHT, SCROLL command 119
- RUN subcommand 278
- run time
 - environment, displaying attributes of 252
 - option, TEST(ERROR, ...), for PL/I 230
 - options module, CEEUOPT 50
- run-time options
 - specifying the STORAGE option 77
 - specifying the TRAP(ON) option 77
 - specifying with COBOL and PL/I 77
- running a program 124
- running in batch mode
 - considerations, TEST run-time option 74
- running your program, introduction to 14
- RUNTO command
 - using, to replay recorded statements 126

S

- save file 323
- saving
 - setup file using Debug Tool Utilities 72
- scope of objects in C and C++ 248
- scroll area, Debug Tool 115
- SCROLL command
 - using 119
- searching for characters or strings 120
- self-modifying code, restrictions for debugging 266, 271
- separate debug file 25
- separate debug file, data set 322
- separate debug file, finding renamed 133
- session
 - variables, for PL/I 230
- session panel
 - changing colors and highlighting in 196
 - changing window layout 194
 - command line 114
 - description 107
 - header fields 108
 - navigating 119
 - opening and closing windows 195
 - order in which Debug Tool accepts commands from 115
 - PF keys
 - initial settings 117
 - using 117
- session panel (*continued*)
 - windows
 - scrolling 119
- session panel, while debugging assembler 262
- session settings
 - changing in Debug Tool 193
- session variables
 - declaring, for COBOL 215
- SET AUTOMONITOR ON command, example 129
- SET commands
 - SET AUTOMONITOR
 - using to record breakpoints 124
 - viewing output from 111
 - SET AUTOMONITOR ON
 - monitoring values of variables 128
 - SET DEFAULT SCROLL
 - using 109
 - SET EQUATE
 - using 194
 - SET INTERCEPT
 - using with C and C++ programs 246
 - SET PFKEY
 - using in Debug Tool 117
 - SET QUALIFY
 - using with COBOL 219
 - using, for C and C++ 253
 - SET REFRESH
 - using 287
 - SET SCROLL DISPLAY OFF
 - using 109
 - SET WARNING
 - using with PL/I 234
- setting
 - line breakpoint 124
- setting breakpoints, in C++ 255
- setting breakpoints, introduction to 14
- settings
 - changing Debug Tool profile 197
 - changing Debug Tool session 193
- setup file
 - copying JCL into, using DTSU 70
 - creating, using Debug Tool Utilities 69
 - editing, using DTSU 69
 - saving, using Debug Tool Utilities 72
- setup files
 - overview of 8
- side files, how Debug Tool locates 325
- single terminal mode (CICS) 284
- size, reducing program 289
- sizing session panel windows 195
- source file in window, changing 120
- source file, finding renamed 133
- source files, how Debug Tool locates 325
- Source window
 - changing source files 120
 - description 110
 - displaying halted location 121
 - retrieving lines from 118
- source, program
 - displaying with Debug Tool 110
- start Debug Tool, implications of when to 23

- starting
 - a debugging session in full-screen mode through a VTAM terminal 103
 - Debug Tool from DB2 stored procedures 103
 - Debug Tool in full-screen mode, introduction to 12
 - your program from Debug Tool Utilities 72
- starting a full-screen debug session 101
- starting Debug Tool
 - __ctest(), using 86
 - batch mode 91
 - DB2 program with TSO 278
 - from a Language Environment program 79
 - starting your program for a debug session 95
 - under CICS 95, 96, 99
 - under CICS, using CEEUOPT 98
 - under IMS 282
 - under MVS in TSO 89
 - using the TEST run-time option 73
 - with PLITEST 85
 - with the CEETEST function call 79
 - within an enclave 311
- Starting Debug Tool
 - at different points 74
- starting Debug Tool Utilities 9
- starting interactive function calls in C 168
- starting your program 101
- statement tables, removing 290
- statements
 - PL/I 227, 230
 - recording and replaying, introduction to 17
- stdout, capturing output to
 - in C 168
 - in C++ 180
- STEP command
 - using, to replay recorded statements 126
- stepping
 - through a program 124
 - through C++ programs 255
- stepping, introduction to 14
- stopping
 - Debug Tool session 18
- storage
 - classes, for C 249
- storage errors, finding overwrite
 - in assembler 192
 - in C 170
 - in C++ 182
 - in COBOL 146
 - in PL/I 162
 - uninitialized
 - in C 171
 - in C++ 182
- STORAGE run-time option, specifying 77
- storage, raw
 - C, displaying 169
 - C++, displaying 180

- storage, raw (*continued*)
 - COBOL, displaying 144
 - PL/I, displaying 160
- stored procedures
 - DB2, debugging 279
- string substitution, using 194
- strings
 - C, displaying 169
 - C++, displaying 180
 - searching for in a window 120
- substitution, using string 194
- symbol tables, removing 290
- syntax diagrams
 - how to read xvi
- SYSDEBUG 322
- SYSTCPD 335
- system commands, issuing, Debug Tool 116

T

- template in C++ 255
- terminology, Debug Tool xv
- TEST compiler option
 - benefit of using 337
 - debugging C when only a few parts are compiled with 168
 - debugging C++ when only a few parts are compiled with 179
 - debugging COBOL when only a few parts are compiled with 143
 - debugging PL/I when only a few parts are compiled with 159
 - for C 37
 - for C++ 41
 - for COBOL 25
 - for DB2 50
 - for PL/I 33
 - restrictions 338
 - specifying NUMBER option with 26
 - suboptions 25
 - syntax of C 338
 - syntax of C++ 339
 - syntax of COBOL 340
 - syntax of PL/I 343
 - using #pragma statement to specify 40
 - using for IMS 63
- TEST run-time option
 - as parameter on RUN subcommand 278
 - example of 76
 - for PL/I 230
 - specifying with #pragma 78
 - suboption processing order 73
- this pointer, in C++ 179
- trace, generating a COBOL run-time paragraph 145
- traceback, COBOL routine 144
- traceback, function
 - in assembler 191
 - in C 169
 - in C++ 181
 - in PL/I 160
- tracing run-time path
 - in C 170
 - in C++ 181

- tracing run-time path (*continued*)
 - in COBOL 144
 - in PL/I 161
- TRAP, Language Environment run-time option 134, 303
- TRAP(ON) run-time option, specifying 77
- trigraph 204
- trigraphs
 - using with C 204
- TSO
 - starting Debug Tool using TEST run-time option 101
- TSO command
 - using to debug DB2 program 277
- TSO, starting Debug Tool under 89

U

- uninitialized storage errors, finding
 - in C 171
 - in C++ 182
- UNIX System Services
 - compiling a C program on 39
 - compiling a C++ program 42
 - compiling a Enterprise PL/I program on 34
 - using Debug Tool with 293
- unsupported
 - HLL modules, coexistence with 308
 - PL/I language elements 234
- UP, SCROLL command 119
- USE file 74
- using Debug Tool
 - finding renamed source, listing, or separate debug file 133

V

- values
 - assigning to C and C++ variables 239
 - assigning to COBOL variables 211
- variable
 - modifying value
 - in C 166
 - in C++ 177
 - in COBOL 141
 - in PL/I 158
 - using SET AUTOMONITOR ON command to monitor value of 128
 - value, displaying 127
- variables
 - accessing program, for C and C++ 238
 - accessing program, for COBOL 211
 - assigning values to, for C and C++ 239
 - assigning values to, for COBOL 211
 - compatible attributes in multiple languages 306
 - displaying, for C and C++ 238
 - displaying, for COBOL 213
 - HLL 300
 - qualifying 301

- variables (*continued*)
 - session
 - declaring, for C and C++ 240
 - session, for PL/I 230
 - viewing and modifying data members in C++ 179
 - VS COBOL II programs, debugging 220
 - VS COBOL II, finding list for 220
 - VTAM
 - starting a debugging session through a, terminal 103

W

- warning, for PL/I 234
- what you need to debug 24
- window id area, Debug Tool 115
- window, error numbers in 133
- windows, Debug Tool session panel
 - changing configuration 194
 - opening and closing 195
 - resizing 195
 - zooming 196
- workstation debugging
 - See* remote debug mode

Z

- zooming a window, Debug Tool 196

Readers' Comments — We'd Like to Hear from You

Debug Tool for z/OS
Debug Tool Utilities and Advanced Functions for z/OS
User's Guide
Version 5 Release 1

Publication No. SC18-9302-04

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	☐	☐	☐	☐	☐

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	☐	☐	☐	☐	☐
Complete	☐	☐	☐	☐	☐
Easy to find	☐	☐	☐	☐	☐
Easy to understand	☐	☐	☐	☐	☐
Well organized	☐	☐	☐	☐	☐
Applicable to your tasks	☐	☐	☐	☐	☐

Please tell us how we can improve this book:

Thank you for your responses. May we contact you? ☐ Yes ☐ No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Name

Address

Company or Organization

Phone No.



Cut or Fold
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
Reader Comments
DTX/E269
555 Bailey Ave.
San Jose, CA
95141-9989



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Printed in USA

SC18-9302-04

