

z/OS  
Version 2 Release 3

*TSO/E Programming Guide*



**Note**

Before using this information and the product it supports, read the information in [“Notices” on page 137.](#)

This edition applies to Version 2 Release 3 of z/OS (5650-ZOS) and to all subsequent releases and modifications until otherwise indicated in new editions.

Last updated: 2019-02-16

© **Copyright International Business Machines Corporation 1988, 2017.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>List of Figures.....</b>	<b>ix</b>
<b>List of Tables.....</b>	<b>xi</b>
<b>About this document.....</b>	<b>xiii</b>
Who should use this document.....	xiii
How this document is organized.....	xiii
How to use this document.....	xiii
Where to find more information.....	xiii
<b>How to send your comments to IBM.....</b>	<b>xv</b>
If you have a technical problem.....	xv
<b>Summary of changes.....</b>	<b>xvi</b>
Summary of changes for TSO/E for Version 2 Release 3 (V2R3) and its updates.....	xvi
Summary of changes for z/OS Version 2 Release 2 (V2R2).....	xvi
z/OS Version 2 Release 1 summary of changes.....	xvi
<b>Part 1. Introduction.....</b>	<b>1</b>
Chapter 1. Programming Using TSO/E.....	3
What is a REXX Exec?.....	3
What is a CLIST?.....	4
What is a command processor?.....	4
Considerations for Writing REXX Execs, CLISTs and command processors.....	5
Storing REXX Execs in VLF Storage.....	6
Controlling REXX Exec Compression.....	6
What is an APPC/MVS Transaction Program?.....	7
What is a Server?.....	8
Overview of TSO/E Programming Services.....	8
Syntax Notational Conventions.....	9
<b>Part 2. Writing a command processor.....</b>	<b>11</b>
Chapter 2. What is a command processor?.....	13
The TSO/E Environment.....	13
The command processor parameter list (CPPL).....	13
Accessing the user profile table without a CPPL.....	14
Command Syntax.....	15
What is a Subcommand Processor?.....	16
Chapter 3. Writing a command processor.....	17
Chapter 4. Validating command operands.....	19
Using the parse service routine.....	19
Checking positional operands for logical errors.....	20
Checking unidentified keyword operands.....	20
Using the prompt mode HELP.....	21
A sample command processor.....	22
Chapter 5. Communicating with the Terminal User.....	27
Issuing Messages.....	27
Message Levels.....	27

Using the I/O Service Routines to Handle Messages.....	27
Using the TSO/E Message Issuer Routine (IKJEFF02).....	28
Using generalized routines for issuing messages.....	28
Performing Terminal I/O.....	28
Changing Your Command Processor's Source of Input.....	29
Writing a Full-Screen command processor.....	29
Set Full-Screen Mode On.....	31
Give Control to the command processor.....	31
Write to and Get Information from the Terminal.....	31
Exiting and Reentering Full-Screen Mode.....	32
Full-Screen command processor Termination.....	33
Examples of Full-Screen command processor Operation.....	33
Chapter 6. Passing Control to Subcommand Processors.....	39
Step 1. Issuing a Mode Message and Retrieving an Input Line.....	39
Step 2. Validating the Subcommand Name.....	39
Step 3. Passing control to the subcommand processor.....	40
Writing a subcommand processor.....	40
Step 4. Releasing the Subcommand Processor.....	40
Chapter 7. Processing Abnormal Terminations.....	41
Error handling routines.....	41
ESTAE and ESTAI Exit Routines.....	41
When are Error Handling Routines Needed?.....	41
Guidelines for Writing ESTAE and ESTAI Exit Routines.....	42
Linkage Considerations.....	43
Chapter 8. Processing Attention Interruptions.....	45
Responding to Attention Interruptions.....	45
How Attention Interruptions are Processed.....	45
Deferring Attention Exits.....	46
System Use of STAX DEFER=YES.....	47
Writing Attention Handling Routines.....	47
Parameters Received by Attention Handling Routines.....	48
Full-Screen Protection Responsibilities of Attention Exit Routines.....	50
Chapter 9. Creating HELP Information.....	51
Writing HELP Members.....	52
Format of HELP Members.....	52
The prompt mode HELP function.....	54
An Example of a HELP Member.....	54
Chapter 10. Installing a command processor.....	57
Using a Private Step Library.....	57
Placing Your command processor in SYS1.CMDLIB.....	57
Creating Your Own Command Library.....	57
Chapter 11. Executing and Testing a command processor.....	59
Executing a command processor.....	59
Testing an Unauthorized command processor.....	59
Testing a command processor That is Terminating Abnormally.....	59
Testing a command processor not currently executing.....	59
Testing an authorized command processor.....	60
<b>Part 3. Preparing, Executing and Testing a Program.....</b>	<b>61</b>
Chapter 12. Overview of Preparing, Executing and Testing a Program.....	63

Chapter 13. Compiling and Assembling Programs.....	67
ASM Command.....	67
COBOL Command.....	67
FORT Command.....	67
PLI Command.....	67
RUN Command.....	68
Compiling Source Code Statements.....	68
Passing Parameters When Compiling.....	68
Specifying a Subroutine Library When Compiling - the LIB Operand.....	69
Specifying VSBASIC Compiler Options.....	69
Chapter 14. Binding or Link-Editing a Program.....	71
LINK Command.....	71
Creating a Program Object or Load Module.....	71
Resolving External References - the LIB Operand.....	72
Producing Output Listings - the PRINT Operand.....	72
Creating a Map of the Program Object or Load Module - the MAP Operand.....	73
Producing a List of All Binder or Linkage Editor Control Statements - the LIST Operand.....	73
Producing a Cross Reference Table - the XREF Operand.....	74
Producing a Symbol Table - the TEST Operand.....	74
Sending Error Messages to Your Terminal - the TERM/NOTERM Operand.....	74
Chapter 15. Loading and Executing a Program.....	75
LOADGO Command.....	75
Loading and Executing Programs with No Operands.....	75
Passing Parameters when Loading and Executing Programs.....	76
Requesting Output Listings when Loading and Executing Programs - the PRINT/NOPRINT and TERM/NOTERM Operands.....	76
Resolving External References when Loading and Executing Programs - the CALL/NOCALL and LIB Operands.....	76
Specifying an Entry Point when Loading and Executing Programs - the EP Operand.....	77
Specifying Names when Loading and Executing Programs - the NAME Operand.....	77
CALL Command.....	77
Loading and Executing Load Modules.....	77
Passing Parameters when Loading and Executing Load Modules.....	78
Chapter 16. Testing a Program.....	79
The TEST and TESTAUTH Commands.....	79
The TEST Command.....	79
The TESTAUTH Command.....	79
Using TEST or TESTAUTH.....	79
When to Use the TEST and TESTAUTH Commands.....	80
Testing a Currently Executing Program.....	80
Testing a program not currently executing.....	80
Testing an APPC/MVS Transaction Program.....	81
Examples of Issuing the TEST and TESTAUTH Commands.....	82
Example 1.....	82
Example 2.....	82
Example 3.....	82
Example 4.....	82
Example 5.....	83
Example 6.....	83
Example 7.....	83
Example 8.....	83
Example 9.....	83
Example 10.....	84
TEST and TESTAUTH Subcommands.....	84

Addressing Conventions Associated with TEST and TESTAUTH.....	85
Absolute Address.....	86
Relative Address.....	86
Symbolic Address.....	86
[Module-Name].Entry-Name.....	86
Qualified Addresses.....	86
General Registers.....	87
Floating-Point Registers.....	87
Vector Registers.....	87
Vector Mask Register.....	88
Access Registers.....	88
Indirect Address.....	88
Address Expression.....	89
Restrictions on the Use of Symbols.....	90
External Symbols.....	90
Internal Symbols.....	91
Addressing Considerations.....	91
Examples of Valid Addresses in TEST and TESTAUTH Subcommands.....	91
Programming Considerations for Using TEST and TESTAUTH.....	92
Considerations for 31-Bit addressing.....	92
Considerations for Using the Virtual Fetch Services.....	93
Considerations for a Cross-Memory Environment.....	93
Considerations for the Vector Facility.....	93
Considerations for Extended Addressing.....	94
Considerations for Testing Inbound APPC/MVS Transaction Programs.....	94
Considerations for a Tested Program's Environment.....	95
 Chapter 17. A Tutorial Using the TEST Command.....	97
How to Use This Tutorial.....	98
Preparing to Use TEST.....	98
Viewing a Program in Storage.....	100
Monitoring and Controlling Program Execution.....	108
Altering Storage and Registers.....	111
Using Additional Features of TEST.....	114
More TEST Subcommands.....	120
GETMAIN and FREEMAIN.....	120
LOAD and DELETE.....	121
CALL.....	121
Testing Programs That Use the Vector Facility.....	121
Testing Programs That Use Extended Addressing.....	123
Displaying and modifying access registers.....	123
Displaying and modifying data in alternate address spaces.....	123
Copying Data to and from Alternate Address Spaces.....	124
Providing Symbolic Names for Locations in Alternate Address Spaces.....	124
Example programs for the TEST tutorial.....	125
 <b>Appendix A. Accessibility.....</b>	<b>133</b>
Accessibility features.....	133
Consult assistive technologies.....	133
Keyboard navigation of the user interface.....	133
Dotted decimal syntax diagrams.....	133
<b>Notices.....</b>	<b>137</b>
Terms and conditions for product documentation.....	138
IBM Online Privacy Statement.....	139
Policy for unsupported hardware.....	139
Minimum supported hardware.....	140
Trademarks.....	140

<b>Index.....</b>	<b>141</b>
-------------------	------------





---

## List of Figures

1. Interface between the TMP and a command processor .....	13
2. Format of the Command Buffer.....	14
3. Chaining of Control Blocks and Fields to the UPT.....	15
4. A command processor that is using the parse service routine.....	20
5. A sample command processor.....	22
6. Function of RESHOW in Full-Screen Message Processing.....	34
7. Function of INITIAL=YES when First Message is Full-Screenfunctionof INITIAL=YESwhen first message is full-screen.....	35
8. Function of INITIAL=YES when First Message is Non-Full-Screen, Example 1.....	35
9. Function of INITIAL=YES when First Message is Non-Full-Screen, Example 2.....	36
10. Function of INITIAL=NO.....	37
11. Format of the Input Buffer.....	39
12. ABEND, ESTAI, ESTAE Relationship.....	42
13. Parameters Passed to the Attention Exit Routine.....	49
14. Syntax of the SAMPLE Command.....	54
15. Syntax of the EXAMPLE Subcommand.....	54
16. Example of a HELP Member for the SAMPLE Command and EXAMPLE Subcommand.....	55
17. Compiling and Link-Editing a Single Program.....	64
18. Terminal Session Showing Execution of a Single Program.....	65



---

# List of Tables

- 1. Determining When an Exec is Compressed..... 7
- 2. Summary of TSO/E Services..... 8
- 3. The command processor parameter list (CPPL)..... 14
- 4. Mapping Macros for Control Blocks that Chain to the UPT..... 15
- 5. Command processor return codes for register 15..... 18
- 6. Macros Used to Write a Full-Screen command processor..... 30
- 7. The Attention Exit Parameter List..... 50
- 8. The Terminal Attention Interrupt Element..... 50
- 9. Categories of Information in HELP Members..... 52
- 10. Format of a HELP Data Set Member..... 52
- 11. Commands Used to Prepare, Execute and Test a Program..... 63
- 12. Source/Program Product Relationship..... 68
- 13. The TEST and TESTAUTH Subcommands..... 84
- 14. Address Forms Supported by TEST..... 97



## About this document

---

This document supports z/OS (5650-ZOS).

This document describes how to write and install a command processor in the topic about [Part 2, “Writing a command processor,”](#) on page 11, and how to provide HELP information for a command in the topic about [Chapter 9, “Creating HELP Information,”](#) on page 51. It also describes how to compile, assemble, link-edit, execute, and test a program in the TSO/E environment in the topic about [Part 3, “Preparing, Executing and Testing a Program,”](#) on page 61.

## Who should use this document

---

This document is for the following audience:

- Application programmers who design and write programs that run under TSO/E.
- System programmers who modify TSO/E to suit the needs of their installation.

The reader should be familiar with MVS™ programming conventions and the assembler language, and should know how to use TSO/E.

## How this document is organized

---

This document is divided into three parts:

- [Part 1, “Introduction,”](#) on page 1 provides an overview of the types of programs that run under TSO/E and the services TSO/E offers.
- [Part 2, “Writing a command processor,”](#) on page 11 describes how to write and install a command processor, and how to provide HELP information for a command. It discusses the TSO/E services that you can use in a command processor, and refers you to [z/OS TSO/E Programming Services](#) for more information, when needed.
- [Part 3, “Preparing, Executing and Testing a Program,”](#) on page 61 describes how to use TSO/E to compile, assemble, bind or link-edit and execute a program. It also explains how to use the TSO/E TEST and TESTAUTH commands to test a program.

## How to use this document

---

If you have never used this document, read [Chapter 1, “Programming Using TSO/E,”](#) on page 3 to become familiar with the types of programs that you can write to run in the TSO/E environment.

If you are writing a command processor, read [Part 2, “Writing a command processor,”](#) on page 11 of this document, and see [z/OS TSO/E Programming Services](#) for information on the TSO/E services that you can use in your command processor.

If you have written your program, read [Part 3, “Preparing, Executing and Testing a Program,”](#) on page 61 of this document for information on how to compile, assemble, link-edit, execute and test your program.

## Where to find more information

---

Please see [z/OS Information Roadmap](#) for an overview of the documentation associated with z/OS®, including the documentation available for z/OS TSO/E.



## How to send your comments to IBM

---

We invite you to submit comments about the z/OS product documentation. Your valuable feedback helps to ensure accurate and high-quality information.

**Important:** If your comment regards a technical question or problem, see instead [“If you have a technical problem”](#) on page xv.

Submit your feedback by using the appropriate method for your type of comment or question:

### **Feedback on z/OS function**

If your comment or question is about z/OS itself, submit a request through the [IBM RFE Community](http://www.ibm.com/developerworks/rfe/) ([www.ibm.com/developerworks/rfe/](http://www.ibm.com/developerworks/rfe/)).

### **Feedback on IBM® Knowledge Center function**

If your comment or question is about the IBM Knowledge Center functionality, for example search capabilities or how to arrange the browser view, send a detailed email to IBM Knowledge Center Support at [ibmkc@us.ibm.com](mailto:ibmkc@us.ibm.com).

### **Feedback on the z/OS product documentation and content**

If your comment is about the information that is provided in the z/OS product documentation library, send a detailed email to [mhvrcfs@us.ibm.com](mailto:mhvrcfs@us.ibm.com). We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information.

To help us better process your submission, include the following information:

- Your name, company/university/institution name, and email address
- The following deliverable title and order number: z/OS TSO/E Programming Guide, SA32-0981-30
- The section title of the specific information to which your comment relates
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute the comments in any way appropriate without incurring any obligation to you.

IBM or any other organizations use the personal information that you supply to contact you only about the issues that you submit.

## If you have a technical problem

---

If you have a technical problem or question, do not use the feedback methods that are provided for sending documentation comments. Instead, take one or more of the following actions:

- Go to the [IBM Support Portal](http://support.ibm.com) ([support.ibm.com](http://support.ibm.com)).
- Contact your IBM service representative.
- Call IBM technical support.

## Summary of changes

---

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

### Summary of changes for TSO/E for Version 2 Release 3 (V2R3) and its updates

---

This information contains no technical changes for this release.

### Summary of changes for z/OS Version 2 Release 2 (V2R2)

---

The following changes are made for z/OS Version 2 Release 2 (V2R2).

#### **New**

No new content was added.

#### **Changed**

No content was changed.

#### **Deleted**

- Removed information about updating the COMMANDS member in [Chapter 9, “Creating HELP Information,”](#) on page 51.

### z/OS Version 2 Release 1 summary of changes

---

See the Version 2 Release 1 (V2R1) versions of the following publications for all enhancements related to z/OS V2R1:

- *z/OS Migration*
- *z/OS Planning for Installation*
- *z/OS Summary of Message and Interface Changes*
- *z/OS Introduction and Release Guide*



---

## Part 1. Introduction

You can use TSO/E to help you write, execute and test programs. Also, you can write programs to run in the TSO/E environment and use the services provided by TSO/E. The following topics provide an overview of the types of programs that run under TSO/E and the services TSO/E offers.



# Chapter 1. Programming Using TSO/E

There are several types of programs that run under TSO/E: CLISTs, REXX execs, command processors and servers. Although these types of programs are introduced in the following topics, this document gives detailed information on command processors only. For information on writing REXX execs, see [z/OS TSO/E REXX User's Guide](#) and [z/OS TSO/E REXX Reference](#). For a complete discussion of CLISTs, see [z/OS TSO/E CLISTs](#). For more information on writing servers, see [z/OS TSO/E Guide to SRPI](#).

## What is a REXX Exec?

The REstructured eXtended eXecutor (REXX) language is a high-level interpretive language that enables you to write programs in a clear and structured way. You can use the REXX language to write programs, called execs, that perform a given task, or tasks, or group of tasks.

REXX execs have many characteristics that are similar to CLISTs. For example, using either the REXX or CLIST language, you can:

- Perform numerous tasks, including issuing multiple TSO/E commands and invoking programs written in other languages.
- Write structured programs, perform I/O and process arithmetic and character data.
- Write interactive applications by issuing commands of the Interactive System Productivity Facility (ISPF) to display full-screen panels.
- Provide easy-to-use interfaces to applications written in other languages. Execs can prompt the terminal user for information on the tasks the user requests, set up the environment needed for the application, and then issue the commands needed to invoke the application program.

However, a significant difference between REXX execs and CLISTs is that you can execute CLISTs only in a TSO/E environment. REXX execs do not require a TSO/E environment, and can execute in any MVS address space.

TSO/E REXX is the implementation of the Systems Application Architecture® (SAA) Procedures Language on the MVS system. By using the instructions and functions defined for the SAA Procedures Language, you can write REXX execs that will run in any of the supported SAA environments, such as VM/SP (CMS). *SAA Common Programming Interface Procedures Language Level 2 Reference* describes the instructions and functions the SAA Procedures Language offers.

You can also write APPC/MVS transaction programs in the REXX language. The host command environments, CPICOMM, LU62, and APPCMVS, allow you to invoke the SAA common programming interface (CPI) Communications calls and APPC/MVS calls, which are based on the SNA LU 6.2 architecture, respectively. The CPICOMM host command environment allows transaction programs written in the REXX language to be ported across Systems Application Architecture (SAA) environments. The LU62 host command environment allows you to use specific features of MVS in conversations with transaction programs on other systems.

**Note:** APPC/MVS calls that are based on the SNA LU 6.2 architecture are referred to as APPC/MVS calls throughout the document.

For information about writing APPC/MVS transaction programs, see [z/OS MVS Programming: Writing Transaction Programs for APPC/MVS](#). For information about writing and executing REXX execs, see [z/OS TSO/E REXX User's Guide](#) and [z/OS TSO/E REXX Reference](#).

Another advantage to using REXX is that TSO/E provides support for a REXX compiler and run-time library, such as the IBM Compiler and Library for REXX/370. Using a compiler provides significant benefit for programmers during program development and for users when a program is run.

## What is a CLIST?

---

The CLIST language is a high-level interpretive language that you use to work with TSO/E more efficiently. You can write programs, called CLISTs (or command procedures), that perform given tasks or groups of tasks. CLISTs can handle any number of tasks, from issuing multiple TSO/E commands to invoking programs written in other languages.

Because the CLIST language is an interpretive language, CLISTs are easy to test and do not require you to compile or link-edit them. To test a CLIST, you simply run it, correct any errors, and rerun it.

The CLIST language supports a range of programming functions that include:

- CLIST statements to write structured programs, perform I/O, define, and modify variables, and handle errors and attention interruptions.
- Arithmetic and logical operators for processing numeric data.
- String-handling functions for processing character data.

CLISTs can complete a range of tasks. For example, use CLISTs to:

- Allocate data sets that are required for particular programs.
- Write structured applications, use the CLIST language, to call other CLISTs, define common data among nested CLISTs, and pass parameters between CLISTs.

Write interactive applications by issuing commands of ISPF to display full-screen panels.

- Provide easy-to-use interfaces to applications written in other languages. CLISTs can prompt terminal users for information about requesting tasks. CLISTs can set up the environment that is needed for an application, and then issue the commands to use the application program.

For information about creating, using, and testing CLISTs, see [z/OS TSO/E CLISTs](#).

## What is a command processor?

---

TSO/E provides commands that you can use to perform a wide variety of tasks. For example, you can use TSO/E commands to define and maintain data sets, and write and test programs.

You can write *command processors* to replace or add to this set of commands. By writing your own command processors, your installation can add to or modify TSO/E to better suit the needs of its users.

A command processor is a program (written in assembler language, PL/1, or compiled REXX then linked into a load module) that receives control when a user at a terminal enters a command name. It is given control by the terminal monitor program (TMP), a program that provides an interface between terminal users and command processors, and has access to many system services.

The main difference between command processors and other programs is that when a command processor is invoked, it is passed a command processor parameter list (CPPL) that gives the program access to information about the caller and to system services.

Command processors must be able to communicate with the user at the terminal, as well as respond to abnormal terminations and attention interruptions. Command processors can recognize subcommand names entered by the terminal user and then load and pass control to the appropriate subcommand processor.

To write a command processor, you can use many of the services documented in [z/OS TSO/E Programming Services](#). For example, you can use the TSO/E service facility (IKJEFTSR) to invoke other commands, CLISTs or programs. [Part 2, “Writing a command processor,” on page 11](#) provides guidelines about which TSO/E services to use, and how to write, test, and install a command processor.

## Considerations for Writing REXX Execs, CLISTs and command processors

---

Often, you can perform the same programming functions by writing a program that is a command processor, a REXX exec, or a CLIST. For example, you can write any of these types of programs to do the following:

- List all of the users who have exclusive use of a resource, such as a data set
- List all of the data sets having a certain attribute, such as a record format of FB
- Process and display accounting information
- List the members of a partitioned data set

You can often solve application problems by combining the best attributes of REXX execs, CLISTs and command processors. For example, you can write a REXX exec or CLIST that interacts with the user, and then invokes a command processor to perform the primary processing.

Consider the following when deciding whether to implement a function as a command processor, REXX exec or CLIST:

- Environment in which the program executes.

CLISTs and command processors execute in a TSO/E environment only. However, you can write REXX execs to execute in both TSO/E and other environments, because a subset of the REXX language is independent of both operating system software and hardware.

- Features of the programming language used.

A command processor is typically written in assembler language. Thus, you must assemble and link-edit your program before executing it. However, a benefit of assembler language is that a command processor can access system services, such as those provided by data management and supervisor macro instructions.

The REXX and CLIST languages are high-level languages that support a wide range of programming functions. For example, REXX and CLIST allow you to perform I/O, invoke TSO/E commands and perform arithmetic operations. Both languages are interpretive; therefore, you are not required to compile or link-edit the program before executing it.

- Performance considerations.

Because REXX is an interpretive language, each line is scanned, processed, and executed every time the program is run. For large REXX execs, this can result in reduced performance when compared to a program that is in load module form for execution.

If you make your program available to many people, or if the program is used often, you should consider the performance aspect carefully. A large program may be more efficient if it is written as a command processor.

REXX execs that are allocated to the SYSPROC system level file or the SYSPROC application level file are compressed when they are stored in the VLF data repository. In general, compression strips comments and leading and trailing blanks. Blank lines are replaced with null lines. For details on file compression restrictions, see [“Storing REXX Execs in VLF Storage”](#) on page 6.

The compression provides a potential performance benefit by reducing the amount of data being stored in the VLF data space for each REXX exec:

- The reduction in file size means a reduction in the amount of central, expanded, and auxiliary storage used to process the REXX execs.
- There are fewer page-in I/O operations and cross-memory move operations on each invocation of the REXX execs.
- File compression allows for more storage in the repository for the same storage utilization.

## Storing REXX Execs in VLF Storage

---

The author of the REXX exec can control whether a REXX exec allocated to a SYSPROC system-level or application-level CLIST library is to be compressed. In general, compression strips comments and leading and trailing blanks. Blank lines are replaced with null lines. Details on file compression restrictions for REXX are explained below.

**Note:** Automatic compression governed by the occurrence or non-occurrence of SOURCELINE in an exec can be overridden by explicit use of a compression indicator. You can specify either COMMENT or NOCOMMENT in a special comment in line 1 of the exec, as described in [“Controlling REXX Exec Compression”](#) on page 6 to control compression.

When the system compresses a REXX exec, it removes the comment text and leaves the beginning and ending comment delimiters.

### Controlling REXX Exec Compression

The following describes the control that you have over the compression of REXX execs in the VLF repository.

If you do not want an exec to be compressed, you can allocate the exec to either the SYSEXEC file or the SYSPROC user-level file.

If the system finds an explicit occurrence of the characters SOURCELINE outside of a comment in the exec and does not find a special comment with a compression indicator, as explained below, it does not compress the exec. For example, if you use the SOURCELINE built-in function, the system does not compress the exec. If you use a variable called ASOURCELINE1 in the exec, the system does not compress the exec because it locates the characters SOURCELINE within that variable name. Note that the system does compress the exec if the exec contains a "hidden" use of the characters SOURCELINE. For example, you may concatenate the word SOURCE and the word LINE and then use the INTERPRET instruction to interpret the concatenation or you may use the hexadecimal representation of SOURCELINE. In these cases, the system does compress the exec because the characters SOURCELINE are not explicitly found.

The author of a REXX exec can control whether an exec is compressed by specifying a special comment in line 1 of the exec which contains a compression indicator (that is, either COMMENT or NOCOMMENT).

To specify a compression indicator, the first begin-comment delimiter /\* in line 1 of the exec must be immediately followed by the special comment trigger character %. If the REXX processor finds a special comment begin-delimiter /\*%, it scans the remainder of the comment looking for COMMENT or NOCOMMENT. Scanning terminates when one of the following is found:

- An end-comment delimiter \*/
- Another begin-comment delimiter /\*
- End of line 1

The NOCOMMENT compression indicator indicates to the REXX processor that all comment text, except for the comment text within the special comment, is to be removed from the exec at the time it is loaded and before it is stored into VLF. (Comment removal constitutes exec compression.) COMMENT indicates to the REXX processor that the exec should retain its comment text and that no comment text should be removed.

**Note:**

1. Only execs which are invoked as implicit execs and which are found in SYSPROC or an application-level CLIST library defined by the TSO/E ALTLIB command are eligible for compression. (This is true for both execs which are compressed automatically, and those using controlled compression.)

Therefore, execs loaded from SYSEXEC are never compressed.

2. When TSO/E REXX scans the special comment for a compression indicator, any keyword options that are not recognized are ignored. COMMENT and NOCOMMENT are the only recognized keyword options.

3. If both COMMENT and NOCOMMENT are specified within a special comment, only the last one specified is used.
4. Only EBCDIC characters should be used within the special comment.
5. If an exec is compressed, all comment text, except the comment text of the special comment, and leading and trailing blanks within each line of the exec are removed. However, the text of the special comment, up to the first begin-comment delimiter /\*, end-comment delimiter \*/, or end-of-line (whichever is first) is not removed.
  - Although the comment text is removed, the begin-comment delimiter /\* and end-comment delimiter \*/ are not removed. After compression, a typical comment will look like /\*\*/.
  - Blanks and comments within literal strings (delimited by single or double quotation marks) are not removed.
  - Blanks and comments within a DBCS string (delimited by shift-out (X'0E') and shift-in (X'0F')) are not removed.
  - If comment lines are continued across several lines, blanks and text are removed from the line, but the line itself and the begin- and end-comment delimiters are kept to preserve relative line numbering.

Table 1 on page 7 provides an overview of the conditions that cause an exec to be compressed.

Table 1: Determining When an Exec is Compressed.							
Invoked through CALL Instruction or External Function	Invoked through EXEC Explicit Form	Invoked through EXEC Implicit Form					
		User Library	Application- or System-Level Library				
			Exec Library	CLIST Library			
				COMMENT Trigger	NOCOMMENT Trigger	Neither COMMENT nor NOCOMMENT Trigger	
						SOURCELINE String Not Used in Exec	SOURCELINE String Used in Exec
Do NOT Compress	Do NOT Compress	Do NOT Compress	Do NOT Compress	Do NOT Compress	Compress	Compress	Do NOT Compress

## What is an APPC/MVS Transaction Program?

APPC/MVS transaction programs are application programs running on MVS or TSO/E that use special calls to communicate with partner programs on the same MVS system, other MVS systems, or other operating systems in a System Network Architecture (SNA) network. To communicate, the transaction programs hold APPC conversations; in the conversations, they exchange information using specific calls and follow established conversation protocols.

APPC/MVS transaction programs can be involved with TSO/E in the following ways:

- You can write transaction programs in REXX using the LU62, CPICOMM, or APPCMVS host command environments to issue APPC calls to a partner transaction program. For more information on these host command environments, see [z/OS TSO/E REXX Reference](#).
- Programs on MVS, including APPC/MVS transaction programs, can use the TSO/E environment service (IKJTSOEV) to create a TSO/E environment outside of TSO/E. The programs can then use TSO/E services as described in [z/OS TSO/E Programming Services](#).
- Programmers can use the TSO/E TEST and TESTAUTH commands to test certain transaction programs. The commands can be used with inbound transaction programs—those that are initiated in response to

## What is a Server?

inbound conversation requests from their partner transaction programs. These inbound transaction programs are specified on the TEST or TESTAUTH commands and, when requested by their partner programs, are initiated for testing under TSO/E. Outbound APPC/MVS transaction programs are those transaction programs that are not initiated by inbound conversation requests. You can test these transaction programs as ordinary programs using TEST or TESTAUTH (that is, do not specify the TP, LU, BASELU, or KEEPTP keywords). For more information about testing transaction programs on TSO/E, see [z/OS TSO/E Command Reference](#).

For more information about APPC/MVS transaction programs in general, their benefits for cross-system communication and how to write and use transaction programs, see [z/OS MVS Programming: Writing Transaction Programs for APPC/MVS](#).

## What is a Server?

The command processor provides a standard way for application programs to share services. With this facility, programs on properly-configured IBM Personal Computers (PCs) can obtain services from programs on IBM host computers. The PC programs issue service requests and the host programs issue service replies, which the TSO/E Enhanced Connectivity Facilities passes between the systems.

The PC programs that issue service requests are called *requesters*, and the host programs that issue replies are called *servers*. Servers can give PC requesters access to host computer data, commands and resources such as printers and storage. You can write servers to receive service requests, process the requests, and return replies to the requester.

For information on how to write, install, test and debug a server program, see [z/OS TSO/E Guide to SRPI](#).

## Overview of TSO/E Programming Services

TSO/E provides services that your programs can use to perform various tasks. Although some of these services are discussed in this document, see [z/OS TSO/E Programming Services](#) for a complete description.

Table 2 on page 8 lists each TSO/E service and the task it supports.

Table 2: Summary of TSO/E Services	
Task	Service
Invoking TSO/E service routines	CALLTSSR macro instruction
Checking the syntax of subcommand names	Command scan service routine
Checking the syntax of command and subcommand operands	parse service routine
Controlling terminal functions and attributes	Terminal control macro instructions
Processing terminal I/O	BSAM and QSAM TSO/E I/O service routines TGET/TPUT/TPG macros TSO/E Message Handling Routine
Handling attention interruptions	STAX service routine CLIST attention facility
Obtaining a list of data set names	ICQGCLOO
Ensuring that data sets contain enough space	Space management
Changing alternative library environments	Alternative library interface routine
Allocating, concatenating and freeing data sets	Dynamic allocation interface routine



<i>Table 2: Summary of TSO/E Services (continued)</i>	
<b>Task</b>	<b>Service</b>
Retrieving information from the system catalog	Catalog information routine
Constructing a fully-qualified data set name	Default service routine
Analyzing return codes	DAIRFAIL GNRLFAIL/VSAMFAIL
Searching lists of authorized commands, as well as programs and commands not supported in the background	Table look-up service
Invoking commands, CLISTs, REXX execs and programs	TSO/E service facility
Accessing CLIST and REXX variables	Variable access routine
Retrieving information from the names directory	ICQCAL00
Displaying printers	Printer support CLISTs
Invoking Information Center Facility applications	Application invocation function
Retrieving system messages issued during a console session	GETMSG service
Establishing a TSO/E environment outside of the TSO/E TMP	TSO/E environment service

## Syntax Notational Conventions

The following paragraphs describe the notation that this document uses to define the command syntax and format.

1. The set of symbols listed below is used to define the format. Do not type them when you enter the command.

—  
hyphen

\_  
underscore

{ }  
braces

[ ]  
brackets

...  
ellipsis

The special uses of these symbols are explained in the following paragraphs.

2. You can type uppercase letters, numbers, and the set of symbols listed below exactly as shown in the statement definition when you enter the command.

'  
apostrophe

\*  
asterisk

,  
comma

- =  
equal sign
- ()  
parentheses
- .  
period

3. Lowercase letters and symbols appearing in a command definition represent variables for which you can substitute specific information when you enter the command.

For example, if *name* appears in a command definition, you can substitute a specific value (for example, ALPHA) for the variable when you enter the command.

4. Hyphens join lowercase words and symbols to form a *single* variable.

For example, if *member-name* appears in the command syntax, you should substitute a specific value (for example, BETA) for the variable when you enter the command.

5. The default option is indicated by an underscore. If you do not specify anything, you automatically get the default option. For example,

```
LOGOFF      [ DISCONNECT ]  
            [ HOLD       ]
```

indicates you can select DISCONNECT or HOLD. However, if no operand is specified, the default is DISCONNECT.

6. Braces group related items, such as alternatives. You must choose one of the items enclosed within the braces. For example,

```
CALL      { dsname  
           { dsname (membername) } }
```

indicates if you select dsname (membername), the result is CALL dsname (membername).

7. Brackets also group related items. However, everything within the brackets is optional and can be omitted. For example,

```
PROTECT    data-set-name [ PWRITE  ]  
                        [ NOPWRITE ]
```

indicates you can choose one of the items enclosed within the brackets or you can omit both items within the brackets.

8. An ellipsis indicates the preceding item or group of items can be repeated more than once in succession. For example,

```
DELETE (entryname[/ password][...])
```

indicates an entry name and associated optional password you can repeat any number of times in succession.

---

## Part 2. Writing a command processor

TSO/E provides commands that you can use to perform a wide variety of tasks. For example, you can use TSO/E commands to define and maintain data sets, and write and test programs.

You can write command processors to replace or add to this set of commands. By writing your own command processors, your installation can add to or modify TSO/E to better suit the needs of its users.

A command processor is a program that is given control by the terminal monitor program (TMP) when a user at a terminal enters a command name. The TMP provides an interface between terminal users and command processors and has access to many system services.

If you choose to write your own command processors, you can use the command processors and service routines provided by TSO/E to perform many of the functions required by a command processor. The programming services available in TSO/E consist of service routines, macros, SVCs and CLISTs, and are discussed in *z/OS TSO/E Programming Services*.

Part 2, “Writing a command processor,” on page 11 of this document contains several chapters that describe what you must do to write, install, execute and test a . command processor. Chapter 2, “What is a command processor?” on page 13 presents the concepts and terminology that you must understand before you read the later chapters. Chapter 3, “Writing a command processor,” on page 17 outlines the steps to follow when writing a and refers you to later chapters for the details of each step. Read all of command processor. Chapter 2, “What is a command processor?” on page 13 and Chapter 3, “Writing a command processor,” on page 17 and then selectively read the subsequent chapters.



## Chapter 2. What is a command processor?

A command processor is a program invoked by the terminal monitor program (TMP) when a user at a terminal enters a command name. The TMP is a program that accepts and interprets commands, and causes the appropriate command processor to be scheduled and executed. The TMP also communicates with the terminal user, responds to abnormal terminations and processes attention interruptions.

### The TSO/E Environment

When a user logs on to TSO/E, the program specified on the EXEC statement of the user's LOGON procedure is attached during logon processing as the TMP. After the logon is complete, the TMP writes a READY message to the terminal to request that the terminal user enters a command name. The TMP determines whether the user's response is a command name. If a command is entered, the TMP attaches the requested command processor and the command processor then performs the functions requested by the user.

### The command processor parameter list (CPPL)

The interface between the TMP and an attached command processor is shown in [Figure 1 on page 13](#).




Figure 1: Interface between the TMP and a command processor

When the TMP attaches a command processor, register 1 contains a pointer to command processor parameter list (CPPL) containing addresses required by the command processor. The command processor

parameter list CPPL is a four-word parameter list that is located in subpool 1. [Table 3 on page 14](#) describes the contents of the CPPL.

Table 3: The command processor parameter list (CPPL)		
Number of Bytes	Field Name	Contents or Meaning
4	CPPLCBUF	The address of the command buffer for the currently attached command processor.
4	CPPLUPT	The address of the user profile table (UPT). Use the IKJUPT mapping macro, which is provided in SYS1.MACLIB, to map the fields in the UPT.
4	CPPLPSCB	The address of the protected step control block (PSCB). Use the IKJPSCB mapping macro, which is provided in SYS1.MACLIB, to map the fields in the PSCB.
4	CPPLECT	The address of the environment control table (ECT). Use the IKJECT mapping macro, which is provided in SYS1.MACLIB, to map the fields in the ECT.

The first word of the CPPL contains the address of the command buffer for the currently attached command processor. As the TMP receives a line of input from the terminal user, the input is placed into the command buffer. After determining that the user has entered a command name, the TMP attaches the appropriate command processor. [Figure 2 on page 14](#) shows the format of the command buffer.




Figure 2: Format of the Command Buffer

When your command buffer receives control, the fields in the command buffer appear as follows:

- The two-byte length field contains the length of the command buffer, including the four-byte header.
- If the terminal user specified operands, the offset field contains the number of text bytes preceding the first operand. Otherwise, the offset field contains the length of the text portion of the buffer.
- The text field contains the command name, in uppercase characters, followed by any operands the user specified.

## Accessing the user profile table without a CPPL

A program that is invoked in a TSO/E environment may require information from the user profile table (UPT). For example, the language a user has selected is defined by the UPTLANG field of the UPT. The program, however, might not have access to the command processor parameter list (CPPL), which contains the UPT address. A program that does not have access to the CPPL can access the UPT through the protected step control block (PSCB). The PSCB contains the PSCBUPT field, which points to the UPT. MVS provides the mapping macro IKJPSCB for the PSCB.

You can access the PSCB by issuing the EXTRACT macro to request the address of the PSCB. For information about the EXTRACT macro, see *z/OS MVS Programming: Authorized Assembler Services Reference EDT-IXG*.

Figure 3 on page 15 illustrates the two ways a program can access the PSCB.




Figure 3: Chaining of Control Blocks and Fields to the UPT

Figure 3 on page 15 shows the control blocks and fields that support the path to the UPT. MVS provides the mapping macros for these control blocks. Table 4 on page 15 relates the mapping macros to the control blocks shown in Figure 3 on page 15.

Table 4: Mapping Macros for Control Blocks that Chain to the UPT	
Control Block	Mapping Macro
PSA	IHAPSA
TCB	IKJTCB
JSCB	IEZJSCB
PSCB	IKJPSCB
UPT	IKJUPT

## Command Syntax

A command consists of a command name, optionally followed by one or more *operands*. Operands provide the specific information required for the command processor to perform the requested operation. For example, the first two operands for the RENAME command identify the data set to be renamed and specify the new name:

RENAME	OLDNAME	NEWNAME	[ALIAS]
command name	operand_1 (old data set name)	operand_2 (new data set name)	operand_3

There are two types of operands that can follow a command name: *positional* operands and *keyword* operands. Positional operands immediately follow the command name and must be in a specific order. Keyword operands are specific names or symbols that have a particular meaning to the command processor. The terminal user can enter keyword operands anywhere in the command line as long as they follow all positional operands. A keyword operand can have a *subfield* associated with it. A subfield consists of a parenthesized list of positional or keyword operands directly following the keyword.

## What is a subcommand processor?

In the example above, OLDNAME and NEWNAME are positional operands; ALIAS is a keyword operand. The braces around ALIAS indicate that the operand is not required.

The terminal user can enter comments in the command line anywhere a blank might appear by enclosing the text within the delimiters /\* and \*/.

## What is a Subcommand Processor?

---

If your command processor must perform a large number of complex functions, you can divide this work into individual operations. Each operation can be defined and performed by a *subcommand processor*. The user requests one of the operations by first entering the name of the command, and then entering a subcommand to indicate which individual operation should be performed. For example, the TSO/E EDIT command has subcommands. After entering the EDIT command, the user can then enter the subcommands for EDIT.



## Chapter 3. Writing a command processor

This topic describes the steps to follow when writing, installing and using a command processor. Further details are contained in subsequent topics.

### 1. Write the assembler language program.

- Access the command processor parameter list (CPPL).

When a command processor receives control from the TMP, register 1 contains the address of the CPPL. Use the IKJCPPL DSECT, provided in SYS1.MACLIB, to map the fields in the CPPL. Your command processor can then access the symbolic field names within the IKJCPPL DSECT by using the address contained in register 1 as the starting address for the DSECT. The use of the DSECT is recommended since it protects the command processor from any changes to the CPPL.

- Validate any operands entered with the command.

Your command processor must verify that the operands the user specified on the command are valid. Use the parse service routine (IKJPARS) to scan and verify the operands, and prompt the user if operands are incorrect or if required operands are missing. See Chapter 4, “[Validating command operands](#),” on page 19 for a description of the functions provided by the parse service routine.

- Communicate with the user at the terminal.

Your command processor might need to obtain data from the terminal, prompt the user for input, and write messages or data to the terminal. You may also want to display full-screen panels. For information on terminal I/O and full-screen processing, see Chapter 5, “[Communicating with the Terminal User](#),” on page 27.

- Perform the function of the command according to any operands the user specified.

The operands that the user specified on the command indicate which functions your command processor should perform. You can use system services and the services provided by TSO/E to perform many functions. For example, your command processor can use the TSO/E service facility to invoke other commands, programs, CLISTs, or REXX execs.

- Recognize and pass control to any subcommands.

If you have chosen to implement subcommands, your command processor must be able to recognize a subcommand name entered by the terminal user and pass control to the requested subcommand processor. For a description of the steps involved, see Chapter 6, “[Passing Control to Subcommand Processors](#),” on page 39.

- Intercept and process abnormal terminations.

Your command processor must be able to intercept abnormal terminations and perform the processing needed to keep the system operable. For information on writing error handling routines, see Chapter 7, “[Processing Abnormal Terminations](#),” on page 41.

- Respond to and process attention interruptions entered from the terminal.

If your command processor accepts subcommands or operates in full-screen mode, it must be able to respond to an attention interruption entered by the terminal user. Your command processor must provide an attention exit to obtain a line of input from the terminal after an attention interruption occurs. For more information, see Chapter 8, “[Processing Attention Interruptions](#),” on page 45.

- Set the return code in register 15 and return control to the TMP.

When returning control to the TMP, your command processor must follow standard linkage conventions and set a return code in register 15. CLISTs that invoke your command processor can check the return code, which is contained in the variable &LASTCC, to determine whether processing was successful. Your command processor can set one of the following return codes in register 15:

*Table 5: Command processor return codes for register 15*

<b>Return Code Dec(Hex)</b>	<b>Meaning</b>
0(0)	The command processor has executed normally.
12(C)	An error encountered during execution has caused the command processor to terminate. Note that an error does not occur when the command processor is able to obtain the required information by prompting the user.

### 2. **Create HELP information.**

If you plan to make your command processor available to other TSO/E users, provide HELP information about the command, subcommands, and all operands. HELP information is displayed at the terminal when the user enters the HELP command and specifies the name of the command or subcommand. See [Chapter 9, “Creating HELP Information,”](#) on page 51.

### 3. **Assemble the command processor.**

After you code your command processor, you must assemble the source into object code and place it in an object module. For more information, see [Chapter 13, “Compiling and Assembling Programs,”](#) on page 67.

### 4. **Install the command processor .**

For methods that you can use to add your new command processor to TSO/E, see [Chapter 10, “Installing a command processor,”](#) on page 57.

### 5. **Test the command processor and correct errors.**

See [Chapter 11, “Executing and Testing a command processor,”](#) on page 59.

---

## Chapter 4. Validating command operands

When your command processor receives control, it must verify that operands entered with the command are valid and that required operands are specified. This topic introduces the parse service routine and describes how it can be used to determine the validity of command operands. For a complete description of the parse service routine, see [z/OS TSO/E Programming Services](#).

---

### Using the parse service routine

When you write a command processor to run under TSO/E, you need a method to determine whether the command operands specified by the user are syntactically correct. The parse service routine (IKJPARS) checks syntax by searching the command buffer for valid operands. If a required operand is missing, or if the user enters an operand incorrectly, parse can prompt the user. The user can enter question marks to receive any second-level messages that are supplied by your command processor that are associated with the operand. Second-level messages provide more explanation of the initial message. Parse can also display HELP information for an operand after the second-level messages have been issued.

Parse recognizes positional and keyword operands. Positional operands occur first, and must be in a specific order. Keyword operands can be entered in any order when they follow all of the positional operands.

Although parse recognizes comments present in the command buffer, it processes by skipping over them. Comments, which are indicated by delimiter `/*` and `*/`, are not removed from the command buffer.

Before you invoke the parse service routine, your command processor must use the parse macro instructions to create a parameter control list (PCL). The PCL describes the permissible operands. Next, call the parse service routine to compare the information that is supplied by your command processor in the PCL to the operands in the command buffer. Each acceptable operand must have an entry that is built for it in the PCL; an individual entry is called a parameter control entry (PCE).

Parse returns the results of scanning and checking the operands in the command buffer to the command processor in a parameter descriptor list (PDL). The entries in the PDL, called parameter descriptor entries (PDEs), indicate which operands are present in the command buffer. These operands indicate to your command processor the functions the user is requesting.

When your command processor calls the parse service routine, it must pass a parse parameter list (PPL). The PPL contains pointers to control blocks and data areas that are needed by parse. Addresses needed to access the PCL, PDL, and command buffer are included in the parse parameter list.

When the parse server routine finishes processing, it passes a return code in register 15 to your command processor. Your command processor must issue meaningful error messages for all non-zero return codes. To issue meaningful error messages for all non-zero return codes, use the GNRLFAIL routine, in [z/OS TSO/E Programming Services](#).

[Figure 4 on page 20](#) shows the interaction between the command processor and the parse service routine.




Figure 4: A command processor that is using the parse service routine

### Checking positional operands for logical errors

Because the parse service routine checks the command operands only for syntax errors, you must write validity checking routines when it is also necessary to check positional operands for logical errors. Each positional operand can have a unique validity checking routine.

To indicate that a validity checking routine is to receive control, code the entry point address of the routine on the parse macro instruction that describes the operand. The validity checking routine you provide for a positional operand receives control after the parse service routine determines that the operand is specified and is syntactically valid.

When parse passes control to a validity checking routine, it passes a validity check parameter list, which contains the address of the PDE parse built to describe the positional operand. Your validity checking routine can use the information in the PDE to perform additional checking on the operand.

When processing is complete, the validity checking routine must pass a return code in general register 15 to the parse service routine. The return code informs parse of the results of the validity check and determines the action that parse takes.

### Checking unidentified keyword operands

For certain keyword operands, you might want to bypass the syntax checking facility of the parse service routine and provide an alternate method of determining the validity of the operand. To accomplish this, use the parse macro instruction IKJUNFLD and provide a verify exit routine to determine if the operand is valid.

Use the IKJUNFLD macro instruction to indicate that the parse service routine can accept an unidentified keyword operand that is present in the command buffer. An unidentified keyword operand is an operand that is not defined in the parameter control list (PCL). This macro can also be used to indicate that parse can accept unidentified keyword operands within a subfield.

If you code the IKJUNFLD macro instruction, parse accepts unidentified keyword operands, but does not perform any validity checking on them. Your command processor must supply a verify exit routine to perform checking on these operands. Indicate that a verify exit routine is to receive control by coding the entry point address of the routine on the IKJUNFLD macro instruction.

When parse passes control to a verify exit routine, it passes a verify exit parameter list, which contains the address of a parse parameter element that parse built to describe the operand being processed. Your verify exit routine can use this information to examine the operand and determine its validity.

When processing is complete, the verify exit routine must pass a return code in general register 15 to the parse service routine. The return code informs parse of the results of the check and determines the action that parse takes.

## Using the prompt mode HELP

When the parse service routine prompts the user to enter a required operand, or to reenter a syntactically incorrect operand, the user can enter question marks to receive second-level messages associated with the operand. If a question mark is entered and no second-level messages were provided, or they have all been issued in response to previous question marks, parse determines whether it can generate a valid HELP command to provide the user with additional information.

Whether parse can generate a HELP command depends upon the setting of the ECTNOQPR bit in the environment control table (ECT). The ECT is pointed to by the command processor parameter list (CPPL) that is passed to your command processor when it receives control. For information on the ECT, see [Table 3 on page 14](#).

If the ECTNOQPR bit in the ECT is zero, then the prompt mode HELP function is active and parse processing generates a HELP command on the user's behalf. Parse ensures that only one HELP command is issued during a prompting sequence for a given operand. If the user enters another question mark after viewing the on-line usage information, the NO INFORMATION AVAILABLE message is issued.

When your command processor receives control, the ECTNOQPR bit in the ECT is set to zero, which activates the prompt mode HELP function. However, parse sets ECTNOQPR to one before it returns control to the command processor. Therefore, the prompt mode HELP function is not active during subsequent invocations of parse from your command processor or from any subcommands attached by your command processor.

If your command processor accepts subcommands and wants the prompt mode HELP function to be available for a subcommand, it should set ECTNOQPR to zero before attaching the subcommand. The command processor should also ensure that the ECTPCMD and ECTSCMD fields in the ECT contain the command name and the subcommand name, respectively.

If you do not want the prompt mode HELP function to be active, your command processor should set the ECTNOQPR bit to one before it invokes parse for the first time.

To make this function available for your command processor, create a HELP member as described in [Chapter 9, "Creating HELP Information," on page 51](#).

## A sample command processor

The sample command processor in Figure 5 on page 22 demonstrates the use of the parse service routine. A validity checking routine is also provided. The syntax for the sample command is:

```
PROCESS    dsname    [ ACTION    ]
                  [ NOACTION  ]
```

where *dsname* is a positional operand and ACTION/NOACTION are keyword operands. NOACTION is the default if neither ACTION nor NOACTION are specified.

Figure 5: A sample command processor

```
PROCESS    TITLE 'SAMPLE TSO/E COMMAND PROCESSOR'
PROCESS    CSECT ,
PROCESS    AMODE 31          COMMAND'S ADDRESSING MODE
PROCESS    RMODE 31          COMMAND'S RESIDENCY  MODE
*****
*
* TITLE - PROCESS
*
* DESCRIPTION - SAMPLE TSO/E COMMAND PROCESSOR
*
* FUNCTION - THIS SIMPLE COMMAND PROCESSOR DEMONSTRATES THE USE
*            OF THE PARSE SERVICE ROUTINE TO SYNTAX CHECK THE
*            COMMAND OPERANDS.
*
* OPERATION - PROCESS IS A REENTRANT COMMAND PROCESSOR THAT PERFORMS
*            THE FOLLOWING PROCESSING:
*
* 1 - ESTABLISHES ADDRESSABILITY AND SAVES THE CALLER'S REGISTERS
* 2 - ISSUES A GETMAIN FOR DYNAMIC STORAGE
* 3 - USES THE PARSE SERVICE ROUTINE (IKJPARS) TO DETERMINE THE
*     VALIDITY OF THE COMMAND OPERANDS
* 4 - PROVIDES A VALIDITY CHECKING ROUTINE TO PERFORM ADDITIONAL
*     CHECKING OF THE POSITIONAL OPERAND
* 5 - ISSUES A FREEMAIN TO RELEASE THE DYNAMIC STORAGE
* 6 - RESTORES THE CALLER'S REGISTERS BEFORE RETURNING
* 7 - RETURNS TO THE TMP WITH A RETURN CODE IN REGISTER 15
*
*****
PROCESS    CSECT
          STM  R14,R12,12(R13)    SAVE CALLER'S REGISTERS
          LR   R11,R15            ESTABLISH ADDRESSABILITY WITHIN
          USING PROCESS,R11       THIS CSECT
          LR   R2,R1              SAVE THE POINTER TO THE CPPL
*                                AROUND THE GETMAIN
          GETMAIN RU,LV=L_SAVE_AREA  OBTAIN A DYNAMIC WORK AREA
          USING SAVEAREA,R1        AND ESTABLISH ADDRESSABILITY
          ST   R1,8(R13)           PUT THE ADDRESS OF PROCESS'S SAVE
*                                AREA INTO THE CALLER'S SAVE AREA
          ST   R13,B_PTR           PUT THE ADDRESS OF PROCESS'S SAVE
*                                AREA INTO ITS OWN SAVE AREA
          LR   R13,R1              LOAD GETMAINED AREA ADDRESS
          USING SAVE_AREA,R13      POINT TO THE DYNAMIC AREA
          DROP R1                  DON'T USE R1 ANY MORE
          GETMAIN RU,LV=L_WORK_AREA  OBTAIN A DYNAMIC WORK AREA
          USING WORKA,R1           AND ESTABLISH ADDRESSABILITY TO
*                                THE DYNAMIC WORK AREA
          STM  R0,R1,WORK_AREA_GM_LENGTH  SAVE LENGTH AND ADDR OF
*                                DYNAMIC AREA
          LR   R10,R1              GET READY TO USE R10 AS THE
          USING WORKA,R10          DATA AREA SEGMENT BASE REGISTER
          DROP R1
          ST   R2,CPPL_PTR        SAVE THE POINTER TO THE CPPL
*****
*
* MAINLINE PROCESSING
*
```

```

*
*****
*
      XC      RETCODE,RETCODE      INITIALIZE THE RETURN CODE
      GETMAIN RU,LV=L_PPL          OBTAIN A DYNAMIC PPL WORK AREA
      STM     R0,R1,PPL_LENGTH     SAVE LENGTH AND ADDR OF DYNAMIC PPL
      GETMAIN RU,LV=L_ANSWER       OBTAIN A DYNAMIC PPL ANSWER AREA
      STM     R0,R1,ANSWER_LENGTH  SAVE LENGTH AND ADDR OF DYNAMIC PPL
*                                   ANSWER AREA
      L       R2,PPL_PTR           GET THE ADDRESS OF THE PPL
      USING   PPL,R2              AND ESTABLISH ADDRESSABILITY
      L       R1,CPPL_PTR         GET ADDRESS OF CPPL
      USING   CPPL,R1            AND ESTABLISH ADDRESSABILITY
      MVC     PPLUPT,CPPLUPT       PUT IN THE UPT ADDRESS FROM CPPL
      MVC     PPLECT,CPPLECT       PUT IN THE ECT ADDRESS FROM CPPL
      MVC     PPLCBUF,CPPLCBUF     PUT IN THE COMMAND BUFFER ADDRESS
*                                   FROM THE CPPL
      L       R1,WORK_AREA_GM_PTR  GET THE ADDRESS OF THE COMMAND
*                                   PROCESSOR'S DYNAMIC WORK AREA TO
*                                   BE PASSED TO THE VALIDITY CHECK
*                                   ROUTINE
      ST      R1,PPLUWA
*
      DROP   R1
      L       R1,ANSWER_PTR        GET THE ADDRESS OF THE PARSE
*                                   ANSWER AREA AND
*                                   STORE IT IN THE PPL
      ST      R1,PPLANS
      XC      ECB,ECB              CLEAR COMMAND PROCESSOR'S
*                                   EVENT CONTROL BLOCK (ECB)
      LA      R1,ECB              GET THE ADDRESS OF THE COMMAND
*                                   PROCESSOR'S ECB AND
*                                   PUT IT IN THE PPL
      ST      R1,PPL ECB
      L       R1,PCLADCON          GET THE ADDRESS OF THE PCL AND
      ST      R1,PPLPCL           PUT IT IN THE PPL FOR PARSE
      CALLTSSR EP=IKJPARS,MF=(E,PPL) INVOKE PARSE
      DROP   R2
      LTR     R15,R15             IF PARSE RETURN CODE IS ZERO
      BZ      PROCESS             PERFORM PROCESSING FOR THE COMMAND
      MVC     RETCODE(4),ERROR     SET CP RETURN CODE TO 12
      B       CLEANUP            PREPARE TO RETURN TO THE TMP
*
PROCESS DS 0H
*
*
*
*
* CODE TO PERFORM THE FUNCTION OF THE COMMAND PROCESSOR GOES HERE.
* AFTER CALLING THE PARSE SERVICE ROUTINE TO VALIDATE THE COMMAND
* OPERANDS, USE THE PDL RETURNED BY PARSE TO DETERMINE WHICH
* OPERANDS THE USER ENTERED. THEN PERFORM THE FUNCTION REQUESTED
* BY THE USER.
*
*
*
*
*
*****
*
* CLEANUP AND TERMINATION PROCESSING
*
*****
*
CLEANUP DS 0H
      L       R1,PPL_PTR          POINT TO PPL IN DYNAMIC WORK AREA
      FREEMAIN RU,LV=L_PPL,A=(1)  FREE THE STORAGE FOR THE PPL
      L       R1,ANSWER_PTR       POINT TO THE ANSWER PLACE
      L       R1,0(0,R1)         POINT TO THE PDL
      IKJRLSA (R1)              FREE STORAGE THAT PARSE ALLOCATED
*                                   FOR THE PDL
      L       R1,ANSWER_PTR       POINT TO THE ANSWER PLACE
*                                   FREEMAIN RU,LV=L_ANSWER,A=(1) FREE THE STORAGE FOR THE
*                                   ANSWER WORD
      L       R5,RETCODE          SAVE RETURN CODE AROUND FREEMAIN
      L       R1,WORK_AREA_GM_PTR POINT TO MODULE WORK AREA
      FREEMAIN RU,LV=L_WORK_AREA,A=(1)
*                                   FREE THE MODULE WORKAREA
      LR      R1,R13             LOAD PROCESS'S SAVE AREA ADDRESS
      L       R13,B_PTR          CHAIN TO PREVIOUS SAVE AREA
      DROP   R13
      FREEMAIN RU,LV=L_SAVE_AREA,A=(1) FREE THE MODULE SAVEAREA
      L       R14,12(R13)        HERE'S OUR RETURN ADDRESS
      LR      R15,R5             HERE'S THE RETURN CODE
      LM      R0,R12,20(R13)     RESTORE REGS 0-12

```

```

BSM      0,R14                      RETURN TO the TMP

*****
* POSITCHK - IKJPOSIT VALIDITY CHECKING ROUTINE                                *
*                                                                              *
* IF THE DATA SET NAME HAS A PREFIX OF SYS1 THEN THE VALIDITY                *
* CHECKING ROUTINE RETURNS A CODE OF 4 TO PARSE.  THIS RETURN                 *
* CODE INDICATES TO PARSE THAT IT SHOULD ISSUE A MESSAGE TO THE              *
* TERMINAL AND PROMPT THE USER TO RE-ENTER THE DATA SET NAME.               *
*                                                                              *
* IF THE DATA SET PREFIX IS ANYTHING OTHER THAN SYS1, THEN                   *
* THIS ROUTINE RETURNS A CODE OF 0 TO PARSE.                                   *
*                                                                              *
*****
DROP     R10                        WE WILL REUSE REGISTER 10
POSITCHK DS      0D
STM      R14,R12,12(R13)           SAVE PARSE'S REGISTERS
LR       R9,R15
USING    POSITCHK,R9              ESTABLISH ADDRESSABILITY
LR       R2,R1                    SAVE THE VALIDITY CHECK PARAMETER
*                                     LIST PARSE PASSED TO US
* GETMAIN RU,LV=L_SAVE_AREA        OBTAIN A DYNAMIC SAVE AREA FOR
*                                     THE POSITCHK ROUTINE
* USING SAVEAREA,R1                AND ESTABLISH ADDRESSABILITY
* ST      R1,8(R13)                PUT THE ADDRESS OF THIS ROUTINE'S
* ST      R13,B_PTR                SAVE AREA INTO PARSE'S SAVE AREA
*                                     PUT THE ADDRESS OF THIS ROUTINE'S
*                                     SAVE AREA INTO ITS OWN SAVE AREA
*                                     FOR CALLING
* LR      R13,R1                  LOAD ADDRESS OF GETMAINED AREA
* USING   SAVEAREA,R13            AND ESTABLISH ADDRESSABILITY
* L       R10,4(R2)               POINT TO THE COMMAND PROCESSOR'S
* USING   WORKA,R10              ORIGINAL DYNAMIC WORK AREA
* ST      R2,VALCHK_PARAMETER_LIST_PTR DATA AREA SEGMENT BASE REGISTER
*                                     SAVE THE ADDRESS OF THE VALIDITY
*                                     CHECK PARAMETER LIST
* LM      R1,R3,0(R2)             GET THE ADDRESS OF THE PDE
* STM     R1,R3,VALIDITY_CHECK_PARAMETER_LIST
* XC      POSITCHK_RETCODE,POSITCHK_RETCODE
*                                     MAKE SURE WE START WITH A ZERO
*                                     RETURN CODE
* L       R2,PDEADR               GET THE ADDRESS OF THE PDE
* USING   DSNAME_PTR,R2           AND ESTABLISH ADDRESSABILITY TO
* TM      DSNAME_FLAGS1,QUOTE     OUR MAPPING OF THE PDE
* BNO     DSNOK                   IS THE DATA SET NAME IN QUOTES?
* L       R4,DSNAME_PTR           NO - DATA SET NAME IS OK
* CLC     0(L'SYS1,R4),SYS1       POINT TO THE DSN
* BNE     DSNOK                   IS HIGH LEVEL-DESCRIPTOR SYS1?
* L       R5,FOUR                 NO
* ST      R5,POSITCHK_RETCODE     SYS1 IS INVALID.  SET RC=4
* LR      R1,R13                 SAVE THE RETURN CODE
* L       R13,B_PTR               LOAD ROUTINE'S SAVE AREA ADDRESS
* L       R5,POSITCHK_RETCODE     CHAIN TO PREVIOUS SAVE AREA
* FREEMAIN RU,LV=L_SAVE_AREA,A=(1) LOAD THE RETURN CODE
* L       R14,12(R13)             FREE THE MODULE WORKAREA
* LR      R15,R5                 HERE'S OUR RETURN ADDRESS
* LM      R0,R12,20(R13)          HERE'S THE RETURN CODE
* BSM     0,R14                  RESTORE REGS 0-12
* DROP    R9                     RETURN TO PARSE
* DROP    R10
* DROP    R13
*
*****
* DECLARES FOR CONSTANTS                                                    *
*                                                                              *
*****
PCLADCON DC      A(PCLDEFS)        ADDRESS OF PCL
FOUR     DC      F'4'              USED TO SET/TEST RETURN CODE
EIGHT    DC      F'8'              USED TO SET/TEST RETURN CODE
TWELVE   DC      F'12'             USED TO SET/TEST RETURN CODE
ERROR    DC      F'12'             USED TO SET/TEST RETURN CODE
SYS1     DC      C'SYS1.'          HIGH-LEVEL DESCRIPTOR
*****
* PARSE MACROS USED TO DESCRIBE THE COMMAND OPERANDS                      *
*

```



```

*****
*
PCLSTART DS      0H
PCLDEFS  IKJPARM DSECT=PRDSECT
DSNPCE   IKJPOSIT DSNAME,
          PROMPT='THE NAME OF THE DATA SET YOU WANT TO PROCESS.  +
          ENTER '?' FOR HELP',
          HELP=('A DATA SET NAME WHICH HAS A FIRST-LEVEL QUALIFIER+
          OTHER THAN 'SYS1'.'),
          VALIDCK=POSITCHK
ACTPCE   IKJKEYWD DEFAULT='NOACTION'
          IKJNAME  'ACTION'
          IKJNAME  'NOACTION'
          IKJENDP
LPCL     EQU  *-PCLSTART          LENGTH OF THE PCL
*
*****
*
*  DECLARES FOR DYNAMIC VARIABLES
*
*****
*
WORK_AREA          DSECT
WORKA              DS  0F          START OF DYNAMIC WORK AREA
WORK_AREA_GM_LENGTH DS  F          LENGTH OF WORKAREA
WORK_AREA_GM_PTR   DS  F          ADDRESS OF WORKAREA
PPL_LENGTH         DS  F          LENGTH OF PPL
PPL_PTR            DS  F          ADDRESS OF PPL
ANSWER_LENGTH      DS  F          LENGTH OF PPL ANSWER AREA
ANSWER_PTR         DS  F          ADDRESS OF PPL ANSWER AREA
CPPL_PTR           DS  F          ADDRESS OF THE CPPL FROM TMP
RETCODE            DS  F          THE RETURN CODE
PARSE_RETCODE      DS  F          THE RETURN CODE FROM PARSE
POSITCHK_RETCODE   DS  F          THE RETURN CODE FROM THE POSITCHK
*
ECB                DS  F          CP'S EVENT CONTROL BLOCK
VALCHK_PARAMETER_LIST_PTR DS F    POINTER TO THE VALIDITY CHECK
*
PARAMETER LIST

*****
*
*  MAPPING OF THE PDE BUILT BY PARSE TO DESCRIBE A DSNAME OR DSTHING
*  OPERAND.
*
*****
*
DSNAME_DSTHING DSECT          PDE MAPPING FOR THE FOR DSNAME
*
DSNAME_PTR      DS  F          POINTER TO THE DSNAME
DSNAME_LENGTH_1 DS  H          LENGTH OF THE DATA SET NAME
*
DSNAME_FLAGS1   DS  CL1        EXCLUDING QUOTES
*
*          0... .. THE DATA SET NAME IS NOT PRESENT
*          1... .. THE DATA SET NAME IS PRESENT
*          .0... .. THE DATA SET NAME IS NOT CONTAINED WITHIN QUOTES
*          .1... .. THE DATA SET NAME IS CONTAINED WITHIN QUOTES
*
DSNAME_MEMBER_PTR DS  CL1      RESERVED
DSNAME_LENGTH_2   DS  F          POINTER TO THE MEMBER NAME
DSNAME_LENGTH_2   DS  H          LENGTH OF THE MEMBER NAME
*
DSNAME_FLAGS2     DS  CL1        EXCLUDING PARENTHESES
*
*          0... .. THE MEMBER NAME IS NOT PRESENT
*          1... .. THE MEMBER NAME IS PRESENT
*
DSNAME_PASSWORD_PTR DS  CL1     RESERVED
DSNAME_PASSWORD_PTR DS  F          POINTER TO THE DATA SET PASSWORD
DSNAME_LENGTH_3     DS  H          LENGTH OF THE PASSWORD
DSNAME_FLAGS3       DS  CL1        FLAGS BYTE
*
*          0... .. THE DATA SET PASSWORD IS NOT PRESENT
*          1... .. THE DATA SET PASSWORD IS PRESENT
*
DSNAME_PASSWORD_PTR DS  CL1     RESERVED
L_DSNAME_PDE        EQU *-DSNAME_PTR
*
*****
*
*  MAPPING OF THE PDE BUILT BY PARSE TO DESCRIBE THE KEYWORD OPERAND
*
*****

```

## Sample command processor

```

*****
*
KEYWD_PDE          DSECT
KEYWD_NUM          DS  H          CONTAINS THE NUMBER OF THE IKJNAME
*                               MACRO INSTRUCTION THAT CORRESPONDS
*                               TO THE OPERAND ENTERED/DEFAULTED
*
L_KEYWD_PDE        EQU *-KEYWD_PDE
*
      IKJPPL          PARSE PARAMETER LIST
L_PPL      EQU  *-PPL
*
      IKJCPPL        COMMAND PROCESSOR PARAMETER LIST
L_CPPL      EQU  *-CPPL
*
ANSWER      DSECT
            DS      F          PARSE ANSWER PLACE.  PARSE PLACES A
*                               POINTER TO THE PDL HERE
L_ANSWER EQU *-ANSWER
*
            CVT      DSECT=YES  CVT MAPPING NEEDED FOR CALLTSSR MACRO
*
*****
*                               *
*   EQUATES                               *
*                               *
*****
*
R0      EQU  0
R1      EQU  1
R2      EQU  2
R3      EQU  3
R4      EQU  4
R5      EQU  5
R6      EQU  6
R7      EQU  7
R8      EQU  8
R9      EQU  9
R10     EQU  10
R11     EQU  11          BASE REGISTER
R12     EQU  12
R13     EQU  13          DATA REGISTER
R14     EQU  14          RETURN ADDRESS
R15     EQU  15          RETURN CODE
QUOTE   EQU  X'40'      FULLY-QUALIFIED DATA SET NAME
END      PROCESS

```

## Chapter 5. Communicating with the Terminal User

Your command processor may need to obtain data from the terminal, prompt the user for input, or write messages or data to the terminal. You may also want to use the full-screen capabilities of TSO/E to display full-screen panels.

This topic provides an overview of how to issue messages, perform terminal I/O, change the source of input, and use the full-screen capabilities of TSO/E in your command processor. For additional information on the macros and services discussed in this topic, see [z/OS TSO/E Programming Services](#).

### Issuing Messages

TSO/E supports three classes of messages:

1. *Prompting messages* begin with "ENTER" or "REENTER", and require a response from the user. For example, prompting messages are issued by the parse service routine when the user has entered an incorrect operand or when a required operand is missing.

Issue prompting messages from your command processor to obtain data from the terminal when additional information is required to perform the requested function.

2. *Mode messages* inform the terminal user which command is in control and indicate that the system is waiting for the terminal user to enter a new command or subcommand. For example, the READY message is a mode message.

If you have chosen to implement subcommands, your command processor can issue a mode message to inform the terminal user that the system is waiting for the user to enter a subcommand.

3. *Informational messages* are issued for information only, and do not require a response from the user. Issue informational messages to notify the terminal user of the status of the command being executed. For example, informational messages should be issued if your command processor encounters an error and must terminate.

### Message Levels

Messages that are issued to a TSO/E user should usually have *second-level messages* associated with them. Second-level messages provide additional explanation of the initial message. They are displayed only if the user specifically requests them by entering a question mark (?).

Prompting messages can have any number of second-level messages. However, informational messages can have only one second-level message associated with them. Mode messages cannot have second-level messages.

### Using the I/O Service Routines to Handle Messages

Your command processor can use the I/O service routines provided by TSO/E to issue messages and obtain the user's response.

Use the PUTLINE service routine, which writes a line of data to the terminal, to display informational messages. Use the PUTGET service routine, which writes a line of data to the terminal and obtains a line of input in response, to issue prompting and mode messages.

Both PUTLINE and PUTGET provide support for displaying messages in the user's desired language as specified in the user profile table. The MVS message service must be active to use this support. In addition, a translated version of the message in the specified language must exist.

You can also use PUTLINE and PUTGET to perform the following functions when issuing prompting or informational messages:

- Remove message identifiers before issuing the message. This is done if the terminal user has used the PROFILE command to indicate that message identifiers are not to be displayed.
- Place inserts into message text.
- Chain second-level messages.

The PUTLINE service routine provides special support for second-level messages that are associated with an informational message. Because many informational messages might be displayed at the terminal before the user enters a question mark, PUTLINE saves them for you. The area in which they are saved exists from one PUTGET to another. In other words, whenever the user can enter a new subcommand, the user can enter a question mark instead, requesting all the second-level messages for informational messages issued during execution of the previous subcommand. If the user does not enter a question mark, PUTGET deletes the second-level messages and frees the area they occupy.

Mode messages cannot have second-level messages, because a question mark entered in response to a mode message is defined as a request for the second levels of previous informational messages. If your command processor supports subcommands, you should use the PUTGET service routine to issue all mode messages so that the second level informational messages are properly handled.

When PUTGET returns a line of data from the terminal, this data is placed in a buffer that resides in subpool 1 and is owned by your command processor. Although the buffers returned by PUTGET are automatically freed when your code relinquishes control, you can use the FREEMAIN macro instruction to free these buffers.

### Using the TSO/E Message Issuer Routine (IKJEFF02)

If your command processor issues messages with numerous inserts, you should use the TSO/E message issuer service routine (IKJEFF02) instead of PUTLINE and PUTGET. Using IKJEFF02 has several advantages:

- It simplifies the issuing of messages with inserts because the same parameter list can be used to issue any message.
- This service makes it convenient to place all messages for a command in a single CSECT. This is important when you have to modify message texts.
- It provides support for second-level messages that are associated with informational or prompting messages.

IKJEFF02 also provides support for displaying messages in the user's desired language as specified in the user profile table. The MVS message service must be active to use this support. In addition, a translated version of the message in the specified language must exist.

### Using generalized routines for issuing messages

If your command processor invokes TSO/E services or system services, you should issue informational messages to notify the user if error conditions occur.

You can use DAIRFAIL to analyze return codes from dynamic allocation (SVC 99) and the TSO/E dynamic allocation interface routine (DAIR), and to issue error messages when appropriate. Use the GNRLFAIL/VSAMFAIL routine to issue error messages for VSAM macro failures, subsystem request failures, parse service routine failures, PUTLINE failures, and abend codes.

## Performing Terminal I/O

---

Your command processor may need to write lines of data to the terminal or obtain data from the terminal. This topic discusses how to perform terminal I/O for data other than messages, message responses, and subcommand requests.

There are several methods that you can use to perform terminal I/O.

- **The BSAM or QSAM macro instructions** provide terminal I/O support for programs that run under TSO/E. For example, you can use the PUT or WRITE macro instructions to display data at the terminal, and you can use the GET or READ macro instructions to obtain input from the terminal.

The major benefit of using BSAM or QSAM to process terminal I/O is that these access methods are not device dependent or TSO/E dependent. Therefore, you can incorporate code from existing routines that use BSAM or QSAM into your command processor without having to modify the macro instructions.

- **The GETLINE and PUTLINE service routines** provide the ability to obtain data from the terminal and write data to the terminal, respectively. Use the GETLINE and PUTLINE macro instructions to invoke these I/O service routines.

When GETLINE returns a line of input, this data is placed in a buffer that resides in subpool 1 and is owned by your command processor. Although the buffers returned by GETLINE are automatically freed when your code relinquishes control, you can use the FREEMAIN macro instruction to free these buffers.

Use the PUTLINE macro instruction with the DATA operand to write one or more lines of data to the terminal.

- **The TGET, TPUT, and TPG macro instructions** to perform terminal I/O. Your command processor can use the TPUT macro instruction to write a line of output to the terminal, and can use the TGET macro instruction to read a line of input. However, the TGET, TPUT and TPG macro instructions are intended only for terminal I/O. To allow your command processor to be executed in a background TSO/E session, use the I/O service routines (STACK, GETLINE, PUTLINE and PUTGET).

## Changing Your Command Processor's Source of Input

---

TSO/E maintains a pushdown list or stack that determines the source of input.

The top element of the stack indicates the currently active input source. This stack is initialized by creating the first element, which indicates that the terminal is the current source of input. Therefore, when your command processor receives control, the current source of input is the terminal. When you use the GETLINE, PUTLINE or PUTGET macro instructions, all input is read from the terminal and all output is written to the terminal.

You may want to obtain input from a source other than the terminal, such as a data set containing records to be processed. TSO/E also allows an *in-storage list* to be used as the source of input. An in-storage list can be either a command procedure (CLIST) or a source data set. Use the STACK service routine in your command processor to change the source of input by either adding or removing an element from the input stack. However, your command processor cannot change or delete the first element.

## Writing a Full-Screen command processor

---

If your command processor needs to display panels, it must be able to issue full-screen messages to the terminal and obtain input from the user. When your command processor displays full-screen messages, it must prevent the screen from being overlaid by non-full-screen messages, such as messages sent by the system operator or other TSO/E users. A full-screen command processor must also provide the necessary processing to allow the terminal user to read non-full-screen messages before they are overlaid by full-screen messages.

Use one of the following methods to write a full-screen command processor:

- If your command processor is to execute in an ISPF environment, use ISPF services to receive requests and data from a terminal user and give appropriate responses. For information on using ISPF services, see [z/OS ISPF Services Guide](#).
- If your command processor is to be used outside of an ISPF environment, or if it must perform functions not available through ISPF services, use VTAM® macros for full-screen processing.

This topic outlines the steps for writing a full-screen command processor using VTAM macros, and contains several examples illustrating the processing that occurs when running a full-screen command processor. You must use the following macros when writing a full-screen command processor:

### **STFSMODE**

Set full-screen mode.

### **STLINENO**

Set the line number.

### **STTMPMD**

Set terminal display manager options.

### **TGET**

Get a line from the terminal.

### **TPUT**

Write a line to the terminal.

See [z/OS TSO/E Programming Services](#) for a complete description of each of these macros.

Follow these steps when writing a full-screen command processor:

1. Set full-screen mode on (see [“Set Full-Screen Mode On”](#) on page 31).
2. If replacing a display terminal manager, such as Session Manager, put the command processor in control (see [“Give Control to the command processor”](#) on page 31).
3. Write to and get information from the terminal as necessary (see [“Write to and Get Information from the Terminal”](#) on page 31).
4. Exit and reenter full-screen mode as necessary (see [“Exiting and Reentering Full-Screen Mode”](#) on page 32).
5. Terminate the full-screen command processor and, if it replaced a display terminal manager, return control to the display terminal manager (see [“Full-Screen command processor Termination”](#) on page 33).

[Table 6 on page 30](#) shows the macros used when writing a full-screen command processor.

Table 6: Macros Used to Write a Full-Screen command processor.		
Macro	Meaning	
(1) STFSMODE ON,INITIAL=YES	Set full-screen mode on	
(2) STTMPMD ON	Give control to the command processor	
(3) TPUT FULLSCR	Issue a full-screen message	
TGET ASIS :	Get input from the terminal	
(4) STLINENO LINE=1 :	Clear the screen and exit full-screen mode expecting to reenter it later	
TPUT EDIT :	Issue a non-full-screen message	
STFSMODE ON	Reenter full-screen mode	
TPUT FULLSCR	Issue a full-screen message	
TGET ASIS	Obtain RESHOW request	
TPUT FULLSCR	Reissue the previous full-screen message	
TGET ASIS :	Get input from the terminal	
(5) STLINENO LINE=1	Clear the screen	
STFSMODE OFF	Exit full-screen mode and set defaults	
STTMPMD OFF	Return control to the display terminal manager	
TPUT EDIT :	Display session summary information	

## Set Full-Screen Mode On

Use the STFSMODE macro to set full-screen mode on. This macro prevents unexpected non-full-screen messages from overlaying the screen. For example, unexpected messages from the operator or from other TSO/E users could cause incorrect input to be sent to the command processor. Also, STFSMODE prevents full-screen messages from overlaying unexpected non-full-screen messages before the user has a chance to read them.

To prevent unnecessary protection of the screen contents, specify INITIAL=YES when you use the STFSMODE macro. If you specify INITIAL=YES and the first message is a full-screen message, TSO/VTAM does not display three asterisks at the terminal (which would require the user to press the Enter key). TSO/VTAM sets the INITIAL keyword indicator to NO after the command processor sends the first full screen of information. For subsequent full screens of output that follow non-full screens of output, TSO/VTAM displays the three asterisks at the terminal before processing the full-screen output. For a description of the processing that takes place when INITIAL=YES and INITIAL=NO, see [“Examples of Full-Screen command processor Operation”](#) on page 33.

### TERMINAL BREAK Support for Full-Screen Mode

When a command processor establishes full-screen mode, VTAM treats all devices as if the terminal user had entered the TERMINAL NOBREAK command. If the user specifies TERMINAL BREAK before a full-screen command processor is invoked, VTAM supports the BREAK mode before the command processor enters full-screen mode and whenever the command processor exits from full-screen mode. See [z/OS TSO/E Command Reference](#) for a description of the TERMINAL command.

## Give Control to the command processor

If your command processor replaces a display terminal manager, such as Session Manager, use the STTMPMD macro to put the command processor in control. If you do not use this macro, the display terminal manager traps line-mode messages so the user does not see them in the ordinary way. If your command processor does not replace a display terminal manager, you do not need this macro.

## Write to and Get Information from the Terminal

Use the TPUT and TGET macros to provide interaction between the user and the command processor. TPUT FULLSCR, TPUT NOEDIT, and TPG transmit a full-screen of output to the terminal.

### Unlocking the Keyboard

When a command processor issues a TGET following a TPUT FULLSCR, VTAM unlocks the display keyboard. When a command processor issues a TGET following a TPUT NOEDIT or a TPG, VTAM does not unlock the keyboard. Programs that use TPUT NOEDIT and TPG are responsible for all device command and write-control-character bit settings.

### Receiving Data

TGET ASIS reads a full screen of input containing the user's reply from the terminal. You can also use the NOEDIT keyword on the STFSMODE macro along with the TGET macro to get a full-screen message from the terminal.

### NOEDIT Mode

To obtain a full screen of input (via a TGET macro) that is not edited in any way, the command processor can specify the NOEDIT keyword on STFSMODE. Regardless of the options the command processor specifies on the TGET macro, in NOEDIT mode, VTAM does not edit the data, break it into separate input lines, or modify it. VTAM receives the input from the terminal and puts it on the input queue intact. To establish NOEDIT mode, the command processor must issue:

```
STFSMODE ON,NOEDIT=YES
```

Use of the NOEDIT keyword has no effect on the treatment of TPUTs and TPGs.

### Considerations for Invoking an External Function:

Before a command processor calls an external function or system service, it must check that the full-screen mode and input mode (normal or NOEDIT) are acceptable to the function or service. For example, if the NOEDIT input mode is in effect when control passes to an external routine, and the invoked routine does not change the input mode, TGET returns data in an unedited format.

### Protection of Screen Contents

When non-full-screen messages are issued in full-screen mode, TSO/VTAM clears the screen and sends the non-full-screen messages to the screen. When the next full-screen message is issued, TSO/VTAM protects the screen contents to allow the user time to read the non-full-screen messages. TSO/VTAM protects the screen by displaying three asterisks (\*\*\*) after the last non-full-screen message and unlocking the keyboard. When finished reading the screen, the user presses Enter to allow full-screen processing to resume.

### Restoration of Screen Contents

As part of the screen protection function, TSO/VTAM discards the full-screen message that immediately follows non-full-screen messages, unless issued with the HOLD option of the TPUT macro. To receive the RESHOW code, the full-screen command processor must issue a TGET macro after every TPUT FULLSCR macro.

The RESHOW indicator tells the command processor to completely restore the screen contents. That is, the command processor must reissue the previous full-screen message. For an example of RESHOW processing, see [“Examples of Full-Screen command processor Operation”](#) on page 33.

RESHOW requests can come from VTAM and from terminal users. Terminal users can request a restoration of the screen by pressing the RESHOW key. The VTAM default RESHOW code is X'6E', which represents the PA2 key. If the command processor uses a PF key for the RESHOW key, it must specify the RSHWKEY keyword on the STFSMODE macro when it first turns on full-screen mode. To set the RESHOW key, issue:

```
STFSMODE ON,RSHWKEY=n
```

where *n* is the PF key number. VTAM uses the hexadecimal representation of the specified PF key as the RESHOW code.

## Exiting and Reentering Full-Screen Mode

If the command processor issues non-full-screen messages (or invokes routines that issue non-full-screen messages), it can issue the STLINENO macro to set full-screen mode off and to set the line number for the next non-full-screen message. In so doing, the command processor eliminates the screen protection function and determines where the next non-full-screen message appears. If the line number is set to 1, VTAM clears the screen. When the command processor issues the last non-full-screen message (or when the invoked routine returns control to the command processor), the command processor must issue STFSMODE ON to reestablish full-screen mode. The command processor must issue the STFSMODE macro before it issues the next full-screen message macro.

If the command processor exits full-screen mode, expecting to reenter full-screen mode at a later time before termination, the command processor must use STLINENO to set full-screen mode off. (Use of STFSMODE to set the mode off results in the RESHOW key being set to the default.) After a TGET request, the command processor can issue:

```
STLINENO LINE=n
```

where *n* is the desired line number. The command processor does not have to specify MODE=OFF on the STLINENO macro because that is the default for the MODE keyword.

When all non-full-screen messages are completed, issue STFSMODE ON before issuing the next full-screen message macro. When the command processor returns to full-screen mode, it must issue the TGET macro to read the RESHOW request in the input queue. It can then continue to transmit and receive information from the terminal.



You may want either to clear part of the screen before issuing STLINEO, or to display information that is to remain on the screen after the STLINEO macro is issued. In either case, issue a full-screen TPUT or TPG macro (including the HOLD option) before issuing the STLINEO. The HOLD option specifies that the program that issued the TPG macro cannot continue its processing until the output line is written to the terminal or deleted. Therefore, the full-screen message reaches the terminal before the STLINEO macro takes effect.

### Clearing the Terminal Screen

Because VTAM clears the screen when the line number is set to 1, STLINEO LINE=1 is an efficient way for the command processor to clear the screen. Use of a full-screen TPUT or TPG macro (including the HOLD option) to clear the screen reduces performance because it causes a swap-out of the address space to wait for the I/O to complete.

## Full-Screen command processor Termination

When a TGET is satisfied with data that causes the command processor to begin exit processing, the following termination procedure is recommended:

### **STLINEO LINE=1**

Causes VTAM to clear the screen.

### **STFSMODE OFF**

Exits full-screen mode and resets the RESHOW key and NOEDIT mode to the defaults.

### **STTMPMD OFF**

Returns control to a display terminal manager, such as Session Manager.

### **Non-full-screen TPUTs**

Optional macros that provide session summary information or other types of termination information.

If the command processor issues a TPUT or TPG macro before (or instead of) issuing the STLINEO macro, it must use the HOLD option to guarantee that the message reaches the terminal before VTAM sets full-screen mode off. If the macro is handling a full-screen message, the command processor must issue a TCLEARQ INPUT macro just before termination to clear the RESHOW code that VTAM put on the input queue for screen protection.

## Examples of Full-Screen command processor Operation

Examples show these functions:

- RESHOW in full-screen message processing
- INITIAL=YES on the STFSMODE macro when the first message is a full-screen message
- INITIAL=YES on the STFSMODE macro when the first message is a non-full-screen message
- INITIAL=NO on the STFSMODE macro

Each example consists of a figure followed by an explanation. The heading for each figure lists the three components involved in the processing: the command processor, TSO/VTAM, and the terminal. The items listed under each component relate to that component. The numbers in the left-hand column of the figures refer to the events described in the explanation. The arrows in the figure indicate the flow of the processing.

### Function of RESHOW in Full-Screen Message Processing

Figure 6 on page 34 shows the use of RESHOW when a command processor, operating in full-screen mode, issues a full-screen message while non-full-screen messages are being displayed at the terminal.




Figure 6: Function of RESHOW in Full-Screen Message Processing

The following events occur in [Figure 6 on page 34](#):

- When the user presses the Enter key to send input to the command processor, TSO/VTAM:
  - Clears the screen.
  - Sounds the alarm (if the terminal has an alarm).
  - Displays non-full-screen messages. The operator or some other user could have sent these messages.
- As long as TSO/VTAM receives non-full-screen messages, it displays them, one after another on the screen.
- The command processor's normal processing of input (see step 1) may cause it to send a full-screen message using the TPUT macro. When TSO/VTAM receives the full-screen message, it:
  - Displays three asterisks (\*\*\*) at the terminal.
  - Unlocks the keyboard to ensure that the user has time to view the non-full-screen messages.
  - Discards the full-screen message that the command processor sent.
- After each full-screen message, the command processor issues a TGET macro. When the user presses the Enter key to acknowledge having seen the non-full-screen messages, TSO/VTAM puts a RESHOW request on the input queue to tell the command processor to completely restore the screen contents. The command processor's current TGET picks up this RESHOW request.
- The command processor responds to the RESHOW request by issuing a full-screen TPUT to restore the screen contents. TSO/VTAM displays the message at the terminal.
- The command processor issues a TGET macro.

## Function of INITIAL=YES when the First Message is Full Screen

[Figure 7 on page 35](#) shows a situation in which the command processor specifies INITIAL=YES on the STFSMODE macro and issues a full-screen message as the first message.




Figure 7: Function of INITIAL=YES when First Message is Full-Screen

The following events occur in Figure 7 on page 35:

1. TSO/VTAM displays the READY message at the terminal. In response to the READY message, the user enters a command name, such as ISPF. The command processor receives the command name.
2. The command processor issues the STFSMODE macro with INITIAL=YES.
3. The command processor issues a full-screen message to the terminal. TSO/VTAM sends the message without warning because the command processor specified INITIAL=YES and because its previous interaction with the terminal involved input, not output. There is nothing to protect.
4. The command processor issues a TGET macro.

### Function of INITIAL=YES when the First Message is Non-Full-Screen

#### Example 1

If the command processor specifies INITIAL=YES on the STFSMODE macro, and the first message is a non-full-screen message, VTAM ignores the keyword and protects the screen contents. Figure 8 on page 35 shows this situation when the STFSMODE macro is issued before the non-full-screen message.




Figure 8: Function of INITIAL=YES when First Message is Non-Full-Screen, Example 1

The following events occur in Figure 8 on page 35:

1. TSO/VTAM displays the READY message at the terminal. In response to the READY message, the user enters a command name. The command processor receives the command name.
2. The command processor issues the STFSMODE macro with INITIAL=YES.

3. TSO/VTAM displays a non-full-screen message. This could be a warning from the operator or a message from another user.
4. The command processor sends a full-screen message to the terminal. TSO/VTAM protects the screen contents by sending three asterisks to the terminal and discarding the full-screen message.
5. After each full-screen message, the command processor issues a TGET macro. When the user presses the Enter key to acknowledge having seen the non-full-screen message, TSO/VTAM puts a RESHOW request on the input queue to tell the command processor to completely restore the screen contents. The command processor's current TGET picks up the RESHOW request.
6. The command processor responds to the RESHOW request by issuing a full-screen message to restore the screen contents. TSO/VTAM displays the full-screen message at the terminal.
7. The command processor issues a TGET macro.

### Example 2

If the command processor specifies INITIAL=YES on the STFSMODE macro, and the first message is a non-full-screen message, VTAM ignores the keyword and protects the screen contents. [Figure 9 on page 36](#) shows this situation when the STFSMODE macro is issued after the non-full-screen message.





Figure 9: Function of INITIAL=YES when First Message is Non-Full-Screen, Example 2

The following events occur in [Figure 9 on page 36](#):

1. TSO/VTAM displays the READY message at the terminal. In response to the READY message, the user enters a command name. The command processor receives the command name.
2. TSO/VTAM displays a non-full-screen message. This could be a warning from the operator or a message from another user.
3. The command processor issues the STFSMODE macro with INITIAL=YES.
4. The command processor sends a full-screen message to the terminal. TSO/VTAM protects the screen contents by sending three asterisks to the terminal and discarding the full-screen message.
5. After each full-screen message, the command processor issues a TGET macro. When the user presses the Enter key to acknowledge having seen the non-full-screen message, TSO/VTAM puts a RESHOW request on the input queue to tell the command processor to completely restore the screen contents. The command processor's current TGET picks up the RESHOW request.
6. The command processor responds to the RESHOW request by issuing a full-screen message to restore the screen contents. TSO/VTAM displays the full-screen message at the terminal.
7. The command processor issues a TGET macro.

**Function of INITIAL=NO**

If the command processor specifies INITIAL=NO or INITIAL=NO is the default, TSO/VTAM protects the screen before displaying the first full-screen message. [Figure 10 on page 37](#) shows an example of this situation.



*Figure 10: Function of INITIAL=NO*

The following events occur in [Figure 10 on page 37](#):

1. TSO/VTAM sends a READY message to the terminal. In response to the READY message, the user enters a command name. The command processor receives the command name.
2. The command processor issues the STFSMODE macro with INITIAL=NO.
3. The command processor sends a full-screen message to the terminal. TSO/VTAM protects the screen contents by sending three asterisks to the screen and discarding the full-screen message that the command processor sent.
4. After each full-screen message, the command processor issues a TGET macro. When the user presses the Enter key, TSO/VTAM puts a RESHOW request on the input queue to tell the command processor to completely restore the screen contents. The command processor's current TGET picks up the RESHOW request.
5. The command processor responds to the RESHOW request by issuing a full-screen message to restore the screen contents. TSO/VTAM displays the full-screen message at the terminal.
6. The command processor issues a TGET macro.



## Chapter 6. Passing Control to Subcommand Processors

If you have chosen to implement subcommands, your command processor must be able to recognize a subcommand name entered by a terminal user and pass control to the requested subcommand processor. This topic outlines the steps you must follow to support subcommands.

Command scan, the PUTGET service routine and the parse service routine are discussed in this topic; see *z/OS TSO/E Programming Services* for more information on these services.

To recognize a subcommand name and pass control to the subcommand processor, follow these steps:

1. Use the PUTGET service routine to issue a mode message and retrieve a line of input that may contain a subcommand.
2. Use the command scan service routine to determine if the user has entered a valid subcommand name.
3. Use the ATTACH macro instruction to pass control to the subcommand processor.
4. Use the DETACH macro instruction to release the subcommand processor when it completes.

### Step 1. Issuing a Mode Message and Retrieving an Input Line

Use the PUTGET service routine to issue a mode message to the terminal and return a line of input. A mode message informs the terminal user which command is in control and lets him know that the system is waiting for him to enter a new subcommand. For example, the TEST message issued by the TEST command processor is a mode message.

When PUTGET returns a line of data from the terminal, it places this data in an input buffer that is owned by your command processor. [Figure 11 on page 39](#) shows the format of the input buffer returned by the PUTGET service routine.




Figure 11: Format of the Input Buffer

The two-byte length field contains the length of the returned input line plus the length of the four-byte header. The two-byte offset field is always set to zero on return from the PUTGET service routine.

### Step 2. Validating the Subcommand Name

Use the command scan service routine to determine whether a syntactically valid subcommand name is present in the input buffer (command buffer). Command scan searches the input buffer for a subcommand name, checks the syntax of the name, and updates the offset field in the input buffer. If a valid subcommand name is found, command scan resets the offset field in the input buffer to the number of text bytes preceding the first subcommand operand, if any are present. For example, if the user enters

```
SUBCMD OPERAND1 OPERAND2
```

### Step 3. Passing control to the subcommand processor

the offset field would be set to 7, the number of bytes that precede OPERAND1 in the input buffer.

Although command scan recognizes comments present in the input buffer, it skips over them without processing them. Comments, which are indicated by the delimiters /\* and \*/, are not removed from the input buffer.

When your command processor passes control to command scan, it must pass a parameter list that contains pointers to control blocks and data areas that are needed by command scan. Addresses needed to access the input buffer and the output area filled in by command scan are included in this parameter list.

When command scan returns control to your command processor, check the return code in register 15. If the return code is zero, check the flag field in the output area to determine whether a syntactically valid subcommand name is present. Use the pointer to the subcommand name and the length of the name returned in the output area when you pass control to the appropriate subcommand processor.

### Step 3. Passing control to the subcommand processor

---

After determining that the user has entered a valid subcommand name, use the ATTACH macro instruction to pass control to the requested subcommand processor.

You should code your ATTACH macro to specify that subpool 78 is to be shared with lower-level tasks.

Depending upon the function and complexity of the command processor and the subcommand processor, you may need to specify the ESTAI operand on the ATTACH macro to provide an error handling routine that receives control if the subcommand processor abnormally terminates. For information on error handling, see [Chapter 7, “Processing Abnormal Terminations,” on page 41](#). For information on the ATTACH macro instruction, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Subcommand processors are similar to command processors in many ways, including syntax and the way they receive control. When your command processor attaches the subcommand processor, you must pass a pointer to a command processor parameter list.

### Writing a subcommand processor

When you write a subcommand processor, it is suggested that you follow steps that are similar to the steps you followed to write your command processor. This procedure is listed below:

1. Access the command processor parameter list (CPPL).
2. Validate any operands entered with the subcommand using the parse service routine.
3. Communicate with the user at the terminal.
4. Perform the function of the subcommand according to any operands the user specified.
5. Intercept and process abnormal terminations.
6. Respond to and process attention interruptions entered from the terminal.
7. Set the return code in register 15 and return to the command processor.

These steps are discussed in more detail in [Chapter 3, “Writing a command processor,” on page 17](#).

### Step 4. Releasing the Subcommand Processor

---

When the subcommand processor has completed processing and returned control to your command processor, use the DETACH macro instruction to release it. For information on the DETACH macro instruction, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).



## Chapter 7. Processing Abnormal Terminations

Depending on the function and complexity of your command processor, you may need to provide error handling routines to process abnormal terminations (abends). This topic describes the criteria you should consider to determine whether special processing is needed for error recovery. It also provides guidelines for writing error handling routines.

### Error handling routines

When an abnormal termination occurs, your command processor must be able to provide sufficient recovery to insure that the error condition does not cause the abnormal termination of a user's TSO/E session. Error handling routines give your command processor the ability to intercept an abend and allow it to clean up, bypass the problem, and if possible, attempt to retry execution.

A command processor must be able to recognize and respond to two types of abnormal terminations:

1. The command processor or a program at the same task level, such as command scan or the parse service routine, is terminating abnormally.
2. An attached subtask, such as a subcommand processor, is terminating abnormally.

### ESTAE and ESTAI Exit Routines

Two types of error handling routines are used in writing command processors: ESTAE exits and ESTAI exits.

- An ESTAE exit is established by issuing the ESTAE macro instruction. The function of an ESTAE exit is to intercept abnormal terminations that occur at the current task level.
- An ESTAI exit processes abnormal terminations that occur at the daughter task level. ESTAI exits are established by using the ATTACH macro with the ESTAI operand.

For information on writing ESTAE type exits, see *z/OS MVS Programming: Authorized Assembler Services Guide*.

### When are Error Handling Routines Needed?

Not all command processors require special error handling. In many cases, the error handling routine provided by the TMP is sufficient. However, if your command processor falls into one of the following categories, you should provide an ESTAE exit routine to handle abnormal terminations at the command processor's task level:

- command processors that process subcommands
- command processors that request system resources that are not freed by abend or DETACH
- command processors that process lists. Recovery processing is necessary to allow processing of other elements in the list if a failure occurs while processing one element.
- command processors that use the STACK service routine to change the source of input. The error handling routine should issue the STACK macro to clear the input stack before returning to the TMP. Failure to clear the stack causes CLIST processing to be handled incorrectly.

In addition, if your command processor attaches subcommands, it should also provide an ESTAI exit to intercept abnormal terminations at the subcommand processor's task level. ESTAE and ESTAI exit routines should be used in such a way that the command processor gets control if a subcommand abnormally terminates.

Figure 12 on page 42 shows the relationship between the command processor, subcommand processor, and the error handling routines.




Figure 12: ABEND, ESTAI, ESTAE Relationship

## Guidelines for Writing ESTAE and ESTAI Exit Routines

When you write ESTAE and ESTAI exit routines, observe the following guidelines:

1. Issue an ESTAE macro instruction as early in your command processor as possible. The ESTAE instruction should be issued before the STAX macro instruction is used to establish an attention exit routine.
2. The error handling exit routine should issue a diagnostic error message of the form:

```

1st level    { command-name } ENDED DUE TO ERROR+
              { subcommand-name }
2nd level    COMPLETION CODE IS xxxx

```

Obtain the name supplied in the first-level message from the environment control table (ECT). The code supplied in the second-level message is the completion code passed to the ESTAE or ESTAI exit from abend. You can use the GNRLFAIL service routine to issue the diagnostic error message, although it requires additional storage space (see guideline number “5” on page 43).

The error handling routine should issue these messages so that the original cause of abnormal termination is recorded, in case the error handling routine itself terminates abnormally before diagnosing the error.

When an abend is intercepted, the command processor ESTAE exit routine must determine whether retry is to be attempted. If so, the exit routine must issue the diagnostic message and return, indicating by a return code that an ESTAE retry routine is available. If a retry is not to be attempted, the exit routine must return, and indicate with a return code that no retry is to be attempted.

3. The ESTAE or ESTAI routine that receives control from abend must perform all necessary steps to provide system cleanup.
4. The error handling exit routine should attempt to retry program execution when possible. If the command processor can circumvent or correct the condition that caused the error, the error handling routine should attempt to retry execution. In other cases, however, RETRY has no function and the command processor ESTAE exit should not specify the RETRY option.
5. Storage might not be available when the ESTAE or ESTAI routine receives control. Any storage the routine requires should be acquired before the routine receives control, and be passed to it.

## Linkage Considerations

Your command processor can issue the ESTAE macro, and the ATTACH macro with the ESTAI operand, in either 24-bit or 31-bit addressing mode. The ESTAE and ESTAI exit and recovery routines receive control in the same addressing mode in which the corresponding macros are issued. When the macros are issued in 31-bit addressing mode, ESTAE and ESTAI routines can reside above 16 MB in virtual storage.



## Chapter 8. Processing Attention Interruptions

This topic describes how TSO/E processes attention interruptions, and what you must do to provide an attention exit. Use the STAX service routine to specify and cancel attention exits, and defer the dispatching of attention exits. After reading this topic, see [z/OS TSO/E Programming Services](#) for information on the STAX service routine.

If your command processor accepts subcommands or operates in full-screen mode, provide an attention handling routine to receive control when a user enters an attention interruption from the terminal.

If your command processor does not establish its own attention exit, the TMP's attention exit receives control when a terminal user enters an attention interruption while the command processor is executing. Therefore, simple command processors should not establish an attention handling routine unless the routine provided by the TMP cannot process an attention interruption adequately.

### Responding to Attention Interruptions

TSO/E interprets an attention interruption as a signal that the user wants to halt current program execution, possibly to request a new command or subcommand. If your command processor accepts subcommands, you must provide an attention handling routine to obtain a line of input from the terminal and respond to that input.

Use the STAX service routine to create the control blocks and queues necessary for the system to recognize and schedule installation exits that receive control as a result of attention interruptions. Your command processor provides the address of an attention exit to the STAX service routine by issuing the STAX macro instruction.

Use the STAX service routine to respond to an attention interruption that occurs during the processing of a CLIST that contains a CLIST attention exit. To establish an attention exit, issue the STAX macro with the CLSTATN=YES and IGNORE=YES operands. This allows your attention exit to receive control and enables it to invoke the CLIST attention facility. The CLIST attention facility is a program and a recovery routine that any program can call to process a CLIST attention exit. For information on the CLIST attention facility, see [z/OS TSO/E Programming Services](#).

### How Attention Interruptions are Processed

An attention interruption is a way that a terminal user can interrupt the current processing that the system is performing. Two examples when a user wants to interrupt the current processing are:

- When a user specifies a command to the system but does not supply all required information, the command prompts the user for more information. At this point, the user can enter the required input or press the attention interrupt key. When the user presses the attention interrupt key, the system displays a "|" message (attention accepted) and immediately terminates the processing of the command.
- When a REXX exec has starting executing but before its completion, the user may decide to enter interactive debug mode and start tracing the REXX exec. In this case, the system displays a "|" message and the message ENTER HI TO END, A NULL LINE TO CONTINUE, OR AN IMMEDIATE COMMAND. +. In response, the user can enter REXX commands such as HI (halt interpretation), TS (trace start), or TE (trace end).

In both these cases, the system takes the appropriate action via an attention exit.

In an application program, you can indicate that you want to be notified when an attention interruption occurs to provide your own appropriate action in an attention exit. To do so, you issue the STAX macro instruction.

When you issue STAX, your request is queued, which means that your attention routine can get control along with the other previously identified attention routines in the system.

Remember that when the user presses the attention interrupt key and your exit gets control, it is possible that the user could press the attention interrupt key again. In this case, the system (by default) gives control to the next higher-level attention exit. This happens as long as the user continues to press the attention interrupt key and attention exits are identified to the system. When all attention exits have been exhausted, the user sees a |I message.

Similarly, you can invoke a program that in turn issues the STAX macro. In this case when the user presses the attention interrupt key, your attention exit only gets control when the user presses the attention interrupt key a second time.

Your application program has no control over lower-level (future) attention exits getting control. That is, you cannot inhibit an application program from issuing the STAX macro and processing attention interruptions before you get control. However, you can inhibit higher-level (previous) attention exits from getting control. To do so, you specify the TOPLEVEL=YES operand on the STAX macro. When you code TOPLEVEL=YES and the user presses the attention interrupt key while your exit is in control, the system displays the "|I" message each time that the user presses the attention interrupt key, but it does not give control to a higher-level attention routine; your attention exit remains in control.

The preceding time-oriented view is only part of the order which the system uses to give control to attention exits. Actually, the current MVS task structure plays a part in the order in which attention routines get control. Normally, you need not be concerned with this, unless your application program attaches one or more subtasks that also issue the STAX macro. In this case, the following rules apply:

1. When you attach a subtask that issues the STAX macro, the attention exit that the subtask establishes gets control before your attention exit, regardless of the order in which your task and the subtask established the attention exits.

This rule applies when you attach more than one subtask. The attention exit(s) for each of the subtasks receive control before your attention exit at the higher task.

2. When you attach more than one subtask, the time-oriented view takes effect for the order in which each of the subtasks' attention exits receive control.

Note that the system uses the order in which each subtask issues the STAX macro, not the order in which you attach the subtasks, to control the order in which it gives control to attention exits. This means that you need to synchronize the order that your subtasks issue the STAX macro to guarantee consistency each time that you attach multiple subtasks.

Some other considerations to remember, when establishing attention exits:

- You can establish more than one attention exit for a task. In this case, the time-oriented rule is used to give control to attention exits.
- To cancel the most recent attention exit at the current task level prior to task termination, you can issue the STAX macro without any operands.
- When a task terminates, either normally or abnormally, any attention exits that it established are removed from the system.
- When an attention exit terminates normally, control can be returned to the point of interruption. In this case, TGET, TPUT, and TPG buffers are flushed. If the program attempts to continue processing from the point of interruption, data in these buffers (an input or output record or an output message from the system) is lost.
- Depending on how many attention interrupts are being processed by the system, your attention request may be ignored by the system. In this situation, the system will send a "|A" to your terminal to indicate that your request will be ignored. You may wait a few seconds and retry your request; but do not press the attention key over and over again.

## Deferring Attention Exits

After you have established an attention exit to the system via the STAX macro, it may become necessary for you to postpone the processing of an attention interruption until some processing completes. For

example, you want to invoke a routine, and you do not want that routine interrupted by the user pressing the attention interrupt key. The STAX DEFER=YES operand gives you this ability. When you invoke STAX with the DEFER=YES operand, you in effect postpone any attention exits for the current task and any higher-level tasks.

After you invoke the STAX DEFER=NO operand, any attention interruption that is pending will be processed. That is, your previously identified attention exit will receive control.

## System Use of STAX DEFER=YES

When the user presses the attention interrupt key, the system gives control to your attention exit at the task level at which the attention exit was established. However, before your attention exit gets control, the system will stop (make non-dispatchable) any of that task's subtasks. The only exception to this rule is if a system routine (that is, an SVRB) is currently running on any of the subtasks and did not specify a STAX DEFER=NO. In this case, the system defers the attention interrupt until the system routine completes or issues STAX DEFER=YES.

When your attention exit return control to the system, the system will start (make dispatchable) all of the subtasks under the task at which the attention exit executed.

If, for any reason, your attention exit requires one of the subtasks to be restarted, it is the responsibility of the attention exit to restart the task using the status start facility. Similarly, if the attention exit requires that the subtasks not be restarted on completion of the attention exit, it is the responsibility of the attention exit to use the status stop facility to ensure that the subtasks will not become dispatchable when the attention exit completes processing.

**Note:** When the system stops tasks within a tree structure, they will be stopped in an indeterminate order when any are deferring attention exits. As a result, care must be taken to control intertask dependencies and dependencies on scheduling attention exits. Failure to do so can result in an intertask deadlock that can only be relieved by canceling the TSO/E user.

## Writing Attention Handling Routines

---

Use the STAX service routine in your command processor to provide the address of an attention exit routine that receives control when an attention interruption occurs.

When your attention exit routine receives control, you must issue a mode message to the terminal indicating the name of the program that was interrupted. You must then allow the user to enter a line of input. Use one of the following methods to accomplish this:

- Omit the IBUF or the OBUF operand from the STAX macro instruction that sets up the attention handling exit. Instead, use the PUTGET macro instruction, specifying the TERM operand, to send a mode message to the terminal identifying the program that was interrupted, and to obtain a line of input from the terminal.
- Specify the OBUF operand on the STAX macro instruction without an IBUF operand, or with an IBUF length of 0. The OBUF operand specifies the address of a buffer containing the text of the mode message to be issued to the terminal user who entered the attention interruption. Then issue the PUTGET macro instruction, specifying the ATTN operand. Use the ATTN operand to cause the PUTGET service routine to inhibit the writing of the mode message, because a message was already written to the terminal from the output buffer specified in the STAX macro instruction. The PUTGET service routine merely returns a logical line of input from the terminal.

In either of the above cases, if the user enters a question mark, the PUTGET service routine automatically causes the second level informational message chain (if one exists) to be written to the terminal, puts out the mode message again, and returns a line from the terminal.

**Note:** If you use the IBUF operand on the STAX macro instruction, no logical line processing or question mark processing is performed. If the user returns a question mark, you will have to use the PUTLINE macro instruction to write the second level informational message chain to the terminal. Then issue a

PUTGET macro instruction, specifying the TERM operand, to write a mode message to the terminal and to return a line of input from the terminal.

Whether you use the IBUF operand on the STAX macro instruction or the PUTGET macro instruction to return a line from the terminal, you can use the command scan service routine to examine what the user has entered. Use command scan to determine that the line of input is syntactically correct in the input buffer returned by the PUTGET service routine, or in the attention input buffer (pointed to by the second word of the attention exit parameter list).

If the user enters a null line, the attention handling routine should return to the point of interruption. Note that, with the exception of the TPUT ASID buffers for TCAM, the TGET, TPG, and TPUT buffers are flushed during attention interruption processing. If any data was present in these buffers, it is lost.

If a new command or subcommand is entered, your attention handling routine must:

- Pass the input line to the mainline command processor for processing.
- Post the command processor's event control block to cause active service routines to return to the command processor.
- Exit.

If your command processor must reset the input stack, do so in the command processor mainline. A stack flush in an attention routine may cause severe errors.

### Parameters Received by Attention Handling Routines

The parameter structure received by your attention exit routine is shown in [Figure 13 on page 49](#).






Figure 13: Parameters Passed to the Attention Exit Routine

When your attention handling routine receives control, the general registers contain the following information:

**Register 0**

Irrelevant

**Register 1**

The address of the attention exit parameter list

**Registers 2–12**

Irrelevant

**Register 13**

Save area address

**Register 14**

Return address

**Register 15**

Entry point address of the attention handling routine

The attention exit parameter list pointed to by register 1 contains the address of a terminal attention interruption element (TAIE).

**The Attention Exit Parameter List**

Table 7 on page 50 shows the format of the attention exit parameter list.

*Table 7: The Attention Exit Parameter List*

Number of Bytes	Field Name	Contents or Meaning
4		The address of the terminal attention interrupt element (TAIE)
4		The address of the input buffer you specified as the IBUF operand of the STAX macro instruction. This field is zero if you did not include the IBUF operand in the STAX macro instruction.
4		The address of the user parameter information you specified as the USADDR operand of the STAX macro instruction. This field is zero if you did not include the USADDR operand in the STAX macro instruction.

**The Terminal Attention Interrupt Element (TAIE)**

The first word of the attention exit parameter list contains the address of an eighteen-word terminal attention interrupt element (TAIE). Table 8 on page 50 shows the format of the TAIE. Use the IKJTAIE macro, which is provided in SYS1.MACLIB, to map the TAIE.

*Table 8: The Terminal Attention Interrupt Element*

Number of Bytes	Field Name	Contents or Meaning
2	TAIEMSGL	The length in bytes of the message placed into the input buffer you specified as the IBUF operand on the STAX macro instruction. This field is zero if you did not code the IBUF operand in the STAX macro instruction.
1	TAIETGET	The return code from the TGET macro instruction issued to get the input line from the terminal.
1	TAIEATTN	The terminal attention interrupt element flag that indicates whether the stack contains a CLIST attention exit. When this field is non-zero, a CLIST with an attention exit is in the stack.
4	TAIEIAD	The interruption address, which is the right half of the interrupted PSW. This is the address at which the program (or a previous attention exit) was interrupted.
64	TAIERSAV	The contents of general registers, in the order 0–15, of the interrupted program.

**Full-Screen Protection Responsibilities of Attention Exit Routines**

If you are writing a full-screen mode command processor, you should provide an attention exit routine to maintain screen protection when the user presses the PA1 or attention key. When the terminal user presses the PA1 or attention key, VTAM sets FULLSCR to OFF, the RESHOW key to the default, and NOEDIT mode to NO. If the command processor does not have an attention exit and the user presses the Enter key (in response to the attention indication), the command processor resumes execution at the point of interruption with these default values. If the command processor has an attention exit routine, the exit routine must issue the STFSMODE macro to reestablish full-screen mode, the desired RESHOW key, and NOEDIT mode. In this way, the attention exit routine maintains screen protection.

---

## Chapter 9. Creating HELP Information

If you write a command processor and make the command available to other users, you should also provide help information for the command. The help information you provide should include information about the command's function, syntax, operands, and messages. If the command processor has subcommands, the help information should also include a description of the subcommands and their operands.

You provide help information in a *help data set*. A help data set is a cataloged, partitioned data set consisting of individual members that contain help information for the commands. Each member contains help information for one command and its subcommands. The name of the member is the name of the command itself. For example, if you write a command processor named PRTDATA, you provide help information in the member named PRTDATA. The members of a help data set contain fixed-length 80-character records.

You can provide help information in the SYS1.HELP data set or in a data set that you or your installation creates. TSO/E provides the SYS1.HELP data set that contains help information for TSO/E commands and subcommands. You must be authorized to update SYS1.HELP.

If you use your own help data set rather than SYS1.HELP, you must define the data set to the system. You can concatenate your help data set to the SYS1.HELP data set or concatenate SYS1.HELP to your data set. Allocate the data sets to the system file SYSHELP. You can allocate the data sets either in a logon procedure or using the ALLOCATE command. For example, if your help data set is called MYCOMMS.HELPCOM, you can use the ALLOCATE command as follows:

```
ALLOCATE FILE(SYSHELP) DA('SYS1.HELP' MYCOMMS.HELPCOM) SHR REUSE
```

The help data sets that you concatenate to the SYS1.HELP data set do not have to have the same attributes as SYS1.HELP. However, the first concatenated data set must have the largest block size of the data sets and must specify a fixed block size.

You can also define your help data set using the IKJTSOxx member of SYS1.PARMLIB. In SYS1.PARMLIB, you use the HELP statement to define the help data sets for your installation. You must be authorized to update the IKJTSOxx member of SYS1.PARMLIB. Using SYS1.PARMLIB to define your help data sets is beneficial because you can then use the TSO/E PARMLIB command to dynamically list and change the HELP PARMLIB statement. For information about specifying help data sets using SYS1.PARMLIB, see [z/OS TSO/E Customization](#).

One advantage of using the SYS1.HELP data set is that the system need only search one data set for help information. An advantage of using your own help data set is that you avoid the possibility of overlaying your help information when you install a new release of TSO/E.

In deciding how to provide help information, consider how the HELP command locates the information. When a user issues the HELP command to obtain help for a command or subcommand, HELP locates the information as follows:

- If the SYSHELP file is allocated when the user issues the HELP command, HELP searches only the data sets that are allocated to SYSHELP.
- If the SYSHELP file has not been allocated, HELP searches the data sets defined on the HELP statement in the IKJTSOxx member of SYS1.PARMLIB. Note that SYS1.PARMLIB is used only if no data sets have been allocated to the SYSHELP file.
- If HELP cannot locate the requested help information in the previous two situations, HELP searches the SYS1.HELP data set, if the data set has not already been searched.

## Writing HELP Members

If you choose to add HELP information to SYS1.HELP, use the IEBUPDTE utility program or the TSO/E EDIT command to update SYS1.HELP. SYS1.HELP is a system data set, so it will generally require operator intervention when it is updated.

To add a new member, MBRNAME, to a data set named PRIVATE.HELP using the EDIT command, enter:

```
edit 'private.help(mbrname)' data new
```

### Format of HELP Members

Each of the HELP members, other than the COMMANDS member, contains the following categories of information, each of which can be displayed at the terminal:

*Table 9: Categories of Information in HELP Members*

Type of Information	Purpose
Subcommand list	Lists the names of subcommands. This appears only if the command has subcommands.
Functional description	Provides a brief description of the function of the command or subcommand.
Syntax	Describes the syntax of the command or subcommand.
Message identifier description	Provides information pertaining to messages issued by the command or its subcommands.
Operand description	Provides information on the command operands. It includes individual sections containing brief descriptions of each positional operand, and of each keyword and its subfield operands.

Use the information described in Table 10 on page 52 when you add to SYS1.HELP or set up your own HELP data set. The control characters, beginning in column 1, divide the data set into the categories described in Table 9 on page 52. These control characters allow the HELP command processor to display text according to the operands supplied on the HELP command. Each HELP data set member should contain at least the )F, )X, and )O control characters.

*Table 10: Format of a HELP Data Set Member*

Control Character	Purpose of Statement
)S	Indicates that a list of commands or subcommands follows.
)F	Indicates that the functional discussion of the command or subcommand follows.
)X	Indicates that the syntax description of the command or subcommand follows.
)M	Indicates that message ID information follows. The information is only printed by the HELP command when the MSGID keyword is specified.

Table 10: Format of a HELP Data Set Member (continued)

Control Character	Purpose of Statement
)I <i>membername</i>	<p>This statement includes additional HELP information in the specified member. The include control character, )I, can appear anywhere within a data set member. If the HELP information you plan to add is not available yet, you can specify the control character and later add the information. No error messages are issued.</p> <p>The member name can be up to eight characters long. There must be at least one blank before and after the member name.</p>
)) <i>messageid</i>	<p>Indicates that information follows describing the named <i>messageid</i>. One of these control statements should be present for each message issued by the command. Each statement contains the identifier of the message it describes. Message IDs can be any length and the first character must be alphabetic.</p>
)O	<p>Indicates that the command operands and their descriptions follow. Positional operands must follow immediately after the )O control statement and before the ))keyword control statements.</p>
)P	<p>Indicates that a positional operand description follows. One of these control statements is required for each positional operand within the command. Each statement contains the name of the positional operand it describes.</p>
)) <i>keyword</i> or keyword with alias	<p>Indicates that information follows describing the named keyword. One of these control statements must be present for each keyword operand within the command. Each statement contains the name of the keyword it describes.</p> <p>An example of an alias used with a keyword (taken from the help member for the ALLOC command is):</p> <pre>))DATASET('DSNAME(S)')/*</pre> <p>or</p> <pre>DSNAME('DSNAME(S)')/*</pre> <p>which indicates the name of the data set to be allocated. List of dsnames (with blanks) specifies the data sets are to be concatenated. The * indicates the terminal to be allocated.</p>
= <i>subcommandname</i>	<p>Indicates that information follows concerning the subcommand named after the equal sign. One of these statements is required for each subcommand accepted by the command being described. This statement merely names the subcommand; it does not describe it. Describe the subcommand in the same manner you would describe a command.</p> <p>If the subcommand has an alias name, you may include the alias name on the control statement, in the format            =<i>subcommandname</i>=<i>subcommandalias</i>. No blanks can appear between the subcommand and the alias.</p>
*	<p>Indicates a comment. The data on this statement is not processed or displayed.</p>

All statements, except the =subcommandname statement, can contain additional information. If you include additional information on the statements, the control characters )S, )F, )X, )I, and )O must be followed by at least one blank, and the control character ))keyword must be followed by at least one blank or a left parenthesis. Any information after the membername field on the include, )I, statement is treated as a comment. Use the left parenthesis when the keyword you are describing is followed by operands enclosed in parentheses.

The only restrictions on statements are that columns 72-80 are reserved for sequence numbers, and column one must contain a right parenthesis, an equal sign, an asterisk, or a blank. The sequence numbers are not printed when the HELP command is executed.

## The prompt mode HELP function

The prompt mode HELP function provides the user of your command processor with information from the HELP data set when the parse service routine issues prompt mode messages.

If you want the prompt mode HELP function to be available for your command processor and its subcommands, enter the positional parameter control character )P on the first line of each positional parameter description for the command and its subcommands in the HELP member.

If you do not provide a description for a positional parameter, supply the name of the positional parameter along with the information you want displayed when the user requests information about the parameter. If a description exists, modify it to not repeat information that is provided by the messages. This also applies to the other descriptions in the HELP members.

**Note:** If you insert )P for only some of the positional parameters for a command or subcommand, unpredictable results can occur when parse processing issues a HELP command for one of its positional parameters.

For more information, see [“Using the prompt mode HELP” on page 21](#).

## An Example of a HELP Member

This topic describes how a fictitious command, SAMPLE, whose syntax is described in [Figure 14 on page 54](#), is formatted for entry into the HELP data set or your own private HELP data set.

---

```
SAMPLE      posit1 [, (posit2)][KEYWD1(posit3,posit4)]
```

---

*Figure 14: Syntax of the SAMPLE Command*

---

The SAMPLE command has one subcommand, the EXAMPLE subcommand, whose syntax is shown in [Figure 15 on page 54](#). Both the command and the subcommand can issue messages IKJXX110I and IKJXX111I.

---

```
EXAMPLE      posit10,posit11 [KEYWD10]
                                   [KEYWD11] [KEYWD13(posit12)]
                                   [KEYWD12]
```

---

*Figure 15: Syntax of the EXAMPLE Subcommand*

---

[Figure 16 on page 55](#) shows the statements that present and format information about the SAMPLE command and EXAMPLE subcommand.

---

```

)S      The SAMPLE command has the following subcommands:  EXAMPLE
)F      Functional description of the  SAMPLE command:
        The SAMPLE command is a fictitious command;
        No command processor exists with this name.
        The SAMPLE command is used merely to describe the
        functions of the HELP data set control statements.
)X      The SAMPLE command has the following syntax:
        Describe the syntax of the SAMPLE command here.
)I MBRNAME  Include additional syntax information for the SAMPLE
        command from the indicated HELP member.
)M      The SAMPLE command issues the following messages:
))IKJXX1101 Describe the message IKJXX1101 here.
))IKJXX1111 Describe the message IKJXX1111 here.
)O      The SAMPLE command has the following positional operands:
)P      POSIT1  Describe it here.
)P      POSIT2  Describe it here.
))KEYWD1 Describe the keyword, KEYWD1 here; include a description of
        POSIT3 and
        POSIT4
=EXAMPLE
)F      Functional description of the EXAMPLE subcommand:
        The EXAMPLE subcommand is a fictitious subcommand.
)X      The EXAMPLE subcommand has the following syntax:
        Describe the syntax of the EXAMPLE subcommand here.
)O      The EXAMPLE subcommand has the following positional operands:
)P      POSIT10 Describe it here.
)P      POSIT11 Describe it here.
))KEYWD10 Describe the keyword, KEYWD10 here.
))KEYWD11 Describe the keyword, KEYWD11 here.
))KEYWD12 Describe the keyword, KEYWD12 here.
))KEYWD13 (POSIT12)
        Describe the keyword, KEYWD13, and the positional
        operand, POSIT12, here.

```

---

*Figure 16: Example of a HELP Member for the SAMPLE Command and EXAMPLE Subcommand*

---





---

## Chapter 10. Installing a command processor

After you have completed writing your command processor, you must install it in a way that makes the command available for you, and possibly other users, to execute. This topic describes the methods that you can use to add your new command processor to TSO/E.

As part of the installation process, use the linkage editor to convert the object modules that result from assembling your command processor into a load module that is suitable for execution. The particular data set that contains the load module is determined by the method that you choose to install your command processor. These methods are described in the topics that follow.

However, if you choose to postpone installing your command processor until you have tested it, you can execute it under the control of the TEST command. To prepare to test your command processor, link-edit the object modules that result from assembling your command processor into a partitioned data set. [“Testing a command processor not currently executing” on page 59](#) describes how to invoke the TEST command for a command processor.

---

### Using a Private Step Library

If you are an unauthorized user, you can request that a LOGON procedure be created that defines a private step library on the STEPLIB DD statement. This step library is a partitioned data set that contains the command. Use the linkage editor to enter your command processor as a member of the partitioned data set.

If you are an authorized user and you intend to make your command available to a large number of TSO/E users, this method is not recommended because of the TSO/E performance degradation that results from the additional search time required for each command. However, using a STEPLIB is advantageous if you want to make your command available to only selected TSO/E users. It is also a useful method to temporarily install your command processor while you are testing and refining your code.

---

### Placing Your command processor in SYS1.CMDLIB

If you are an authorized user, you can use the linkage editor to enter your command processor as a member of the partitioned data set SYS1.CMDLIB. Placing your command processor in SYS1.CMDLIB makes it available to all TSO/E users.

---

### Creating Your Own Command Library

If you are an authorized user, you can create your own command library and concatenate it to the SYS1.CMDLIB data set. To do this, create new statements in the link list (LNKLST00 or LNKLSTxx) in SYS1.PARMLIB. Use the linkage editor to enter your command processor as a member of the command library. This method makes your command available to all TSO/E users.

For information about creating new statements in the link list, see [z/OS MVS Initialization and Tuning Reference](#).



## Chapter 11. Executing and Testing a command processor

After you have installed your command processor, you are ready to execute it. If you encounter errors or abnormal terminations while an *unauthorized* command processor is executing, use the TSO/E TEST command to help determine the reasons for the failures. Use the TSO/E TESTAUTH command to test *authorized* command processors.

This topic describes how to execute your command processor and how to invoke the TEST and TESTAUTH commands for a command processor. This topic only introduces the TEST and TESTAUTH commands; if you are not familiar with the functions and subcommands that they support, see [Chapter 16, “Testing a Program,”](#) on page 79.

### Executing a command processor

To execute your command processor, enter the command name followed by the operands that are needed for the function you want performed.

For example, suppose you have written a command called CONVERT, which converts data records from an input data set into another format, places the results into an output data set, and optionally prints the converted data. Assume also that you have defined the command syntax as follows:

```
CONVERT  input-dsname  output-dsname  [ PRINT      ]
                                           [ NOPRINT   ]
```

That is, input-dsname and output-dsname are positional operands and PRINT/NOPRINT are keyword operands where NOPRINT is the default if neither PRINT nor NOPRINT are specified.

To convert the records in INPUT.DATA, place the result in OUTPUT.DATA and print the contents of the output data set, enter the following command:

```
CONVERT  INPUT.DATA  OUTPUT.DATA  PRINT
```

### Testing an Unauthorized command processor

You can use the TSO/E TEST command to test an executing, unauthorized command processor if it abnormally terminates or produces incorrect results. You can also use TEST to step through your command processor to verify that it is executing properly.

#### Testing a command processor That is Terminating Abnormally

If you are executing your command processor, and it has begun to terminate abnormally, you receive a diagnostic message at the terminal followed by a READY message. You then have a choice of terminating your program or testing it. If you issue the TEST command without operands, the TEST command processor receives control and you can use the TEST subcommands to test your program. If your response is anything but TEST, a question mark (?) or TIME, your command processor is abnormally terminated.

#### Testing a command processor not currently executing

You can also use the TEST command to execute and test a command processor that is not currently executing.

## Testing an authorized command processor

Suppose that the load module for the CONVERT command processor described earlier in this topic resides in the partitioned data set *prefix.LOAD*. To test the command processor, enter:

```
TEST (CONVERT) CP
```

Specify the CP keyword on the TEST command to indicate that the program to be tested is a command processor. The TEST routine creates a command processor parameter list (CPPL), and places its address into register 1 before loading the program. If you do not specify the CP keyword, your command processor will fail.

The TEST command prompts you to enter the command and its operands. You could then enter a command such as:

```
CONVERT INPUT.DATA OUTPUT.DATA PRINT
```

When the TEST command processor issues the TEST mode message to the terminal, you can begin using the TEST subcommands to execute and test your program. For more information on how to use the TEST command, see [Chapter 16, “Testing a Program,” on page 79](#) and [Chapter 17, “A Tutorial Using the TEST Command,” on page 97](#).

## Testing an authorized command processor

You can use the TESTAUTH command to execute and test an authorized command processor that is *not* currently executing. Unlike the TEST command, which is used for unauthorized programs, you cannot use the TESTAUTH command to test a currently executing program. However, the TEST and TESTAUTH commands are similar in that they support most of the same operands, subcommands and functions.

Suppose that the load module for an authorized command processor, called AUTHCMD, resides in 'SYS1.LINKLIB'. To test the command processor, enter:

```
TESTAUTH 'SYS1.LINKLIB(AUTHCMD)' CP
```

Specify the CP keyword on the TESTAUTH command to indicate that the authorized program to be tested is a command processor. The TESTAUTH routine creates a command processor parameter list (CPPL), and places its address into register 1 before loading the program. If you do not specify the CP keyword, your command processor will fail.

The TESTAUTH command prompts you to enter the command and its operands. You could then enter a command such as:

```
AUTHCMD operand1 operand2
```

When the TESTAUTH command processor issues the TESTAUTH mode message to the terminal, you can begin using the TESTAUTH subcommands to execute and test your program. For more information about the functions and subcommands of the TESTAUTH command, see [Chapter 16, “Testing a Program,” on page 79](#).

---

## Part 3. Preparing, Executing and Testing a Program

After you have written a program or source code, the next step is to compile or assemble it. The compiler or assembler creates listings that help you diagnose problems in your source statements, and object modules that contain the compiled or assembled code.

If your program requires data from system libraries or from other programs, you can use TSO/E to link-edit a number of object modules together to form a load module.

You can use TSO/E to execute a program in the foreground, or to submit the JCL statements necessary to execute it in the background. A discussion of how to execute background jobs is provided in [\*z/OS TSO/E User's Guide\*](#).

While you are executing your program, you may encounter errors or abnormal terminations (abends). To help determine the cause of errors and to monitor the execution of your program, use the TEST command for unauthorized programs. Use the TESTAUTH command for authorized programs.

Part 3, “Preparing, Executing and Testing a Program,” on page 61 of this document contains several chapters that describe how to:

- Compile or assemble source code
- Link object modules together to form load modules
- Load programs into real storage and execute them
- Debug programs and monitor their execution



## Chapter 12. Overview of Preparing, Executing and Testing a Program

The following figures show the steps and commands you use when executing a program. These commands are discussed in subsequent topics. [Table 11 on page 63](#) presents the commands you can use when executing a program and shows what each command accomplishes.

<i>Table 11: Commands Used to Prepare, Execute and Test a Program</i>					
<b>Command</b>	<b>Compiles</b>	<b>Link- Edits</b>	<b>Loads</b>	<b>Begins Execution</b>	<b>Monitors Execution</b>
RUN For use ONLY with certain program products.	X	X	X	X	
ASM, FORT, PLI, COBOL Command used to compile or assemble; depends on programming language used.	X				
LINK Produces linkage editor listings to help test and debug a program.		X			
LOADGO		X	X	X	
CALL Program must be in executable load module form and must be a member of a partitioned data set.			X	X	
TEST Program must be a link-edited member of a partitioned data set, or an object module in a sequential or partitioned data set.			X	X	X
TESTAUTH Program must be a link-edited member of an APF-authorized library.			X	X	X

[Figure 17 on page 64](#) shows, in diagram form, the compile, link-edit and execution of a PLI language program. The commands, highlighted in dark print, are discussed in later topics. The modules and listings produced by these commands are shown in the boxes.




Figure 17: Compiling and Link-Editing a Single Program

Figure 18 on page 65 shows what you would see at your terminal when you execute this program. The commands you enter are in lower case type and the system responses are in upper case type.



```

READY
pli programs(sample) source print
PL/I OPTIMIZER V1 R4.0
OPTIONS SPECIFIED
S;

NO MESSAGES PRODUCED FOR THIS COMPILATION
COMPILE TIME  0.00 MINS      SPILL FILE=      0 RECORDS, SIZE  4051
READY
list programs.list
IKJ52827I PROGRAMS.LIST
PL/I OPTIMIZING COMPILER      VERSION 1  RELEASE 4.0
OPTIONS SPECIFIED
S;
PL/I OPTIMIZING COMPILER      TSOCALL=
SOURCE LISTING
NUMBER
10000      TSOCALL:
          PROCEDURE OPTIONS(MAIN);
63500      DECLARE (FILEOUT) FILE; /* PLI OUTPUT FILE      */
71000      PUT FILE (FILEOUT) EDIT ('THIS PLI PROGRAM IS EXECUTING')
          (A);
90000      END TSOCALL;
PL/I OPTIMIZING COMPILER      TSOCALL:
NO MESSAGES PRODUCED FOR THIS COMPILATION
COMPILE TIME  0.00 MINS      SPILL FILE=      0 RECORDS, SIZE 4051

READY
link programs(sample) print plibase

READY
list programs.linklist(sample)
IKJ52827I PROGRAMS.LINKLIST(SAMPLE)

          H96-LEVEL LINKAGE EDITOR OPTIONS SPECIFIED TERM
          DEFAULT OPTION(S) USED _SIZE=(262144,49152)
          ****SAMPLE NOW REPLACED IN DATA SET      AMODE 24
          RMODE IS 24
          AUTHORIZATION CODE IS      0.

READY
alloc f(fileout) dsn(*)
READY
call programs(sample)

          THIS PLI PROGRAM IS EXECUTING

READY

```

Figure 18: Terminal Session Showing Execution of a Single Program



---

## Chapter 13. Compiling and Assembling Programs

After you write your source code, you must compile it into object code and place it in an object module (see [Figure 17 on page 64](#)). The command you use to compile your source code depends on which programming language you are using. The third, or descriptive qualifier in the source code data set name should identify the programming language used to help the compiler find and process the data.

There are a number of versions of some compilers. You can usually find information on how to use your version of a compiler with the compiler code or in its accompanying reference material. This manual describes the commands used with several common compilers.

The RUN command, which is designed specifically for use with the program products listed in [Table 12 on page 68](#), compiles, loads, and executes source statements. If you cannot use the RUN command, you need the diagnostic information provided by the other commands, or you need to link your program to other modules, you must issue separate commands to link-edit your object modules into load modules, load these modules into main storage, and begin program execution. These commands, listed in [Table 11 on page 63](#), are described in the following topics.

Some commands used to compile or assemble source statements are:

- ASM
- COBOL
- FORT
- PLI

---

### ASM Command

Using the ASM command, you can process assembler language data sets and produce object modules. For more information about the ASM command, see [z/OS TSO/E Command Reference](#).

---

### COBOL Command

Using the COBOL command, you can compile American National Standard (ANSI) COBOL programs. This command reads and interprets parameters for the OS Full American National Standard COBOL Version 3 or Version 4 compiler. It also allocates required data sets and passes parameters to the compiler. For more information about the COBOL command, see [z/OS TSO/E Command Reference](#).

---

### FORT Command

Using the FORT command, you can compile a FORTRAN IV (G1) program. The FORT command also allocates required data sets and passes parameters to the FORTRAN IV (G1) compiler. For more information about the FORT command, see [z/OS TSO/E Command Reference](#).

---

### PLI Command

Using the PLI command, you can call the PL/I Optimizing compiler. For more information about the PLI command, see [z/OS TSO/E Command Reference](#).

## RUN Command

Use the RUN command to compile, load, and execute the source statements in the data set that you are editing. The RUN command is designed specifically for use with certain program products; it selects and invokes the particular program product needed to process your source statements. [Table 12 on page 68](#) shows which program product is selected to process each type of source statement.

Table 12: Source/Program Product Relationship.	
SOURCE	PROGRAM PRODUCT
ASSEMBLER	Assembler F
COBOL	OS/VS COBOL Release 2.4
FORTRAN	FORTRAN IV (G1)
PL/I	PL/I Checkout Compiler or PL/I Optimizing Compiler
VSBASIC	VSBASIC
<b>Note:</b> User-defined data set types can be executed under the RUN subcommand of the EDIT command if a prompter name was defined by the installation. However, the RUN command does not recognize these same data set types.	

Using the RUN command, you can specify:

- Which data set contains the source code or object module you want to process, and which assembler or compiler you want to use to process your source statements.
- A string of up to 100 characters that is to be passed as parameters to the program you are running.
- The libraries that contain subroutines your program will use during its execution.
- The options you want to use with a VSBASIC program.

The RUN subcommand of the EDIT command is very similar to the RUN command, and you may use it similarly to the way you use the RUN command. Before you use the RUN subcommand, keep in mind:

- Any data sets required by your problem program may be allocated before you enter EDIT mode or may be allocated using the ALLOCATE subcommand of EDIT.
- If you wish to enter a value for "parameters", you should enter this prior to any of the other keyword operands.

### Compiling Source Code Statements

If the data set name follows standard naming conventions, and the descriptive qualifier is the name of the programming language used, you do not need to specify a compiler with the RUN command. If the system cannot determine which compiler to use, you will be prompted for more information. You can, however, specify the compiler on the RUN command.

For example, to compile the source code statements in member SAMPLE of data set PROG1.PLI, enter:

```
RUN PROG1.PLI(SAMPLE)
```

### Passing Parameters When Compiling

To pass parameters to a program, enclose the parameters in single quotes and specify them after the name of the data set.

For example, to specify 13, FRIDAY, CAT as parameters to pass to program PROG1, which was written in PLI, enter:

```
RUN PROG1 '13 FRIDAY CAT' PLI
```

## Specifying a Subroutine Library When Compiling - the LIB Operand

If you use subroutines that reside in a library data set, specify the LIB operand with the name of the library data set enclosed in parentheses.

For example, when running COBOL program PROG1, you need to use library SUBS.LOAD because it contains the subroutines your program calls:

```
RUN PROG1 COBOL LIB(SUBS.LOAD)
```

You can use the LIB operand when using the assembler, FORTRAN, COBOL, and PLI compilers.

## Specifying VSBASIC Compiler Options

When running the VSBASIC compiler, you can use a number of options with the RUN command. Specify the options you want after the data set's descriptive qualifier (in this case, VSBASIC). Following is a list of operands and a description of each:

### **LPREC**

specifies that long precision arithmetic calculations are required by the VSBASIC program.

### **SPREC**

Default specifying that short precision arithmetic calculations are adequate for a VSBASIC program.

### **TEST**

specifies that testing of a VSBASIC program is to be performed.

### **NOTEST**

Default specifying that the TEST function is not desired with a VSBASIC program.

### **STORE**

specifies that the VSBASIC compiler is to store an object program.

### **NOSTORE**

Default specifying that the VSBASIC compiler is not to store an object program.

### **GO**

Default specifying that the VSBASIC program is to receive control after compilation.

### **NOGO**

specifies that the VSBASIC program is not to receive control after compilation.

### **SIZE(value)**

specifies the number of 1000-byte blocks of VSBASIC user area where value is an integer of one to three digits.

### **PAUSE**

specifies that the VSBASIC compiler is to prompt the terminal user between program chains, giving the user the chance to change certain compiler options.

### **NOPAUSE**

Default specifying no prompting between program chains.

### **SOURCE**

Default specifying that new VSBASIC source code is to be compiled.

### **OBJECT**

specifies that the data set name entered is a fully-qualified name of an object data set to be executed by the VSBASIC compiler.

For more information about the RUN command, see [z/OS TSO/E Command Reference](#).



## Chapter 14. Binding or Link-Editing a Program

The binder and linkage editor, invoked by the LINK command, provides a great deal of information to help you test and debug a program. This information includes a cross-reference table and a map of the module that identifies the location of control sections, entry points, and addresses. You can specify which of these types of information you want by including the LIST, MAP, and XREF operands with the LINK command. You can have this information listed at your terminal or saved in a data set.

### LINK Command

Use the LINK command to invoke the binder or linkage editor service program. Basically, the binder or linkage editor converts one or more object modules (the output modules from a compiler or the assembler) into a load module or program object that is suitable for execution.

You can specify all the binder or linkage editor options explicitly or you can accept the default values. The default values are satisfactory for most uses. By accepting the default values, you simplify the use of the LINK command. This topic does not describe every operand available with the LINK command. For more information on the LINK command, see [z/OS TSO/E Command Reference](#).

In some cases, you might want to use the LOADGO command as an alternative to the LINK command. The LOADGO command may better serve your needs if one of the following situations exists:

- The module that you want to process has a simple structure. That is, it is self contained and does not pass control to other modules.
- You do not require the extensive listings produced by the binder or linkage editor.
- You do not want a program object or load module saved in a library.

On the LINK command, you can specify:

- The names of one or more data sets containing your object modules and/or binder or linkage editor control statements.
- The name of the partitioned data set that will contain the program object or load module after processing by the binder or linkage editor.
- One or more names of library data sets the binder or linkage editor is to search to locate object modules referred to by the module being processed; that is, to resolve external references.
- Whether you want the system to produce binder or linkage editor listings and place them in a data set you specify or at your terminal.
- Whether you want the system to produce and include in the PRINT data set:
  - A map of the output module consisting of the control sections, the entry names, and for overlay structures, the segment number.
  - A list of all binder or linkage editor control statements.
  - A cross-reference table.
- Whether you want the system to place in the output module the symbol tables created by the assembler and contained in the input modules.
- Whether you want error messages directed to your terminal as well as to the PRINT data set.

### Creating a Program Object or Load Module

To create a program object or load module by binding or link-editing an object module, issue the LINK command and specify the object module name. If you want to bind or link more than one object module, issue the LINK command and list the object modules' names separated by commas and enclosed in parentheses.

## LINK command

For example, to bind or link-edit sequential data set object modules FIRST.OBJ, SECOND.OBJ and FIFTH.OBJ, enter:

```
LINK (FIRST,SECOND,FIFTH)
```

The specified data sets will be concatenated within the output program object or load module in the sequence that they are included in the list of data set names. If there is only a single name in the data set list, parentheses are not required around the name. To bind or link-edit object modules in members, enclose the member names in parentheses.

For example, to bind or link members ONE, TWO, and THREE of data set D00ABC.SAMPLE.OBJ, enter:

```
LINK (SAMPLE(ONE),SAMPLE(TWO),SAMPLE(THREE))
```

If the data set name is D00ABC.OBJ, enclose the member names within two pairs of parentheses, for example:

```
LINK ((ONE),(TWO),(THREE))
```

You may substitute an asterisk (\*) for a data set name to indicate that you will enter binder or linkage editor control statements from your terminal. The system prompts you to enter the control statements, which should begin in column 2. Press the Enter key after you enter each control statement. Enter a null line to indicate the end of your control statements.

When you bind or link-edit an object module that is a sequential data set, the binder or linkage editor generates a load module in a partitioned data set and assigns the program object or load module the member name TEMPNAME.

To store the output from the LINK command in a data set, use the LOAD operand with the user-specified qualifier of the data set enclosed in parentheses.

For example, to store the results of the previous example in data set SALES.LOAD(ONE), enter:

```
LINK (FIRST,SECOND,FIFTH) LOAD(SALES(ONE))
```

If you omit the LOAD operand, the system generates a name according to the data set naming conventions. The default descriptive qualifier for the data set name is LOAD.

## Resolving External References - the LIB Operand

To have the system search specific library data sets to resolve any external references in your program, specify the LIB operand, followed by the name of the library data set(s) enclosed in parentheses.

When you specify more than one name, separate the names by a valid delimiter.

For example, to have the system search library data sets MYLIB, YOURLIB, and OURLIB to resolve any external references, enter:

```
LINK SECOND LIB(MYLIB,YOURLIB,OURLIB)
```

If you specify more than one name, the data sets are concatenated to the file name of the first data set in the list. For control statements, the first data set in the list must be preallocated with the ddname or file name SYSLIB before issuing the LINK command. If you specify more than one name, the data sets concatenated to the file name of the first data set lose their individual identity. For details on dynamic concatenation, see *z/OS MVS Programming: Authorized Assembler Services Guide*.

## Producing Output Listings - the PRINT Operand

To have the system produce binder or linkage editor output listings and place them into a data set, use the PRINT operand with the name of the data set enclosed in parentheses.



For example, to have the system produce binder or linkage editor listings from object modules FIRST.OBJ, SECOND.OBJ, and FIFTH.OBJ and place them in data set PRINT.DATA, enter:

```
LINK (FIRST,SECOND,FIFTH) PRINT(PRINT.DATA)
```

To have the system produce binder or linkage editor output listings and display them at your terminal, use the PRINT operand with an asterisk enclosed in parentheses.

For example, to have the system produce binder or linkage editor listings from object modules FIRST.OBJ, SECOND.OBJ, and FIFTH.OBJ and display them at your terminal, enter:

```
LINK (FIRST,SECOND,FIFTH) PRINT(*)
```

When you omit the data set name on the PRINT operand, the data set that is generated is named according to the data set naming conventions. The default descriptive qualifier for the data set name is LINKLIST. This is the default value if you specify the LIST, MAP, or XREF operand. If you want to have the listings displayed at your terminal, you may substitute an asterisk (\*) for the data set name.

To have the system produce no binder or linkage editor output listings, use the NOPRINT operand.

For example, to have the system not produce binder or linkage editor listings from object modules FIRST.OBJ, SECOND.OBJ, and FIFTH.OBJ, enter:

```
LINK (FIRST,SECOND,FIFTH) NOPRINT
```

NOPRINT causes the MAP, XREF, and LIST options to become not valid. NOPRINT is the default value if both PRINT and NOPRINT are omitted, and you do not use the LIST, MAP, or XREF operand.

## Creating a Map of the Program Object or Load Module - the MAP Operand

To have the system include a map of the program object or output module use the MAP and PRINT operands. The program object or output module consists of the control sections, the entry names, and (for overlay structures) the segment number in the PRINT data set. NOMAP, specifying that you do not want a map of the program object or output module, is the default.

For example, to have the system include a map of the output module from object module SECOND into PRINT data set PRINT.DATA, enter:

```
LINK SECOND PRINT(PRINT.DATA) MAP
```

## Producing a List of All Binder or Linkage Editor Control Statements - the LIST Operand

To have the system include a list of all binder or linkage editor control statements and place them in the PRINT data set, use the PRINT and LIST operands. NOLIST, which specifies that you do not want a list of all binder or linkage editor control statements, is the default.

For example, to produce a list of all the binder or linkage editor control statements from object module SECOND.OBJ, and place them in PRINT data set PRINT.DATA, enter:

```
LINK SECOND PRINT(PRINT.DATA) LIST
```

To produce a list of all the binder or linkage editor control statements from object module SECOND.OBJ, and place them in data set SECOND.LINKLIST, where SECOND.OBJ contains both binder or linkage editor control statements and the object module, enter:

```
LINK SECOND LIST
```

## **Producing a Cross Reference Table - the XREF Operand**

To have the system create a cross reference table and place it in the PRINT data set, use the PRINT and XREF operands. The cross reference table includes the module map and a list of all address constants referring to other control sections. Because the XREF operand includes a module map, both XREF and MAP cannot be specified for a particular LINK command. NOXREF, which specifies that you do not want a cross reference table in the PRINT data set, is the default.

For example, to produce a cross reference table from object module SECOND.OBJ, and place it in PRINT data set PRINT.DATA, enter:

```
LINK SECOND PRINT(PRINT.DATA) XREF
```

## **Producing a Symbol Table - the TEST Operand**

To have the system place a symbol table created by the assembler and contained in the input modules into the output module, use the TEST operand. NOTEST, specifying that you do not want a symbol table, is the default.

For example, to have the system place a symbol table created by the assembler and contained in the input module SECOND into the output module, enter:

```
LINK SECOND TEST
```

## **Sending Error Messages to Your Terminal - the TERM/NOTERM Operand**

You can choose whether you want error messages directed to your terminal as well as to the PRINT data set. TERM, which specifies that the system direct error messages to your terminal as well as to the PRINT data set, is the default. If you do not want error messages directed to your terminal, use the NOTERM operand.

For example, enter:

```
LINK SECOND NOTERM
```

---

## Chapter 15. Loading and Executing a Program

Before running a program, you must place the program into main storage. Placing a program into main storage is called *loading* the program. To load and execute a program, use either the LOADGO or CALL command. The LOADGO command loads object modules produced by a compiler or assembler, and program objects and load modules produced by the binder or linkage editor. If you want to load and execute a single program object or load module, the CALL command is more efficient.

---

### LOADGO Command

Use the LOADGO command to load a compiled or assembled program into main storage and begin execution. The LOADGO command invokes the system loader to accomplish this function. The loader combines basic editing and loading services of the binder or linkage editor and program fetch in one job step. Therefore, the *load* function is equivalent to the *link-edit and go* function.

The LOADGO command does not produce objects or load modules for program libraries, and it does not process binder or linkage editor control statements such as INCLUDE, NAME, or OVERLAY. If you need to use these control statements, use the LINK and CALL commands.

The LOADGO command also searches a specified call library (SYSLIB) or a resident link pack area, or both, to resolve external references.

Using the LOADGO command, you can specify:

- The names of one or more data sets containing your program objects or object modules and/or load modules.
- Parameters to pass to the program you execute.
- Whether the system is to produce output listings and place them in a data set you specify or display them at your terminal.
- One or more names of library data sets to be searched by the binder or linkage editor to locate object modules referred to by the module being processed; that is, to resolve external references.
- Whether the system is to send error messages to your terminal as well as to the PRINT data set.
- Whether the system is to include a list of external names and their addresses in the PRINT data set.
- Whether the system is to search the data set(s) you specified on the LIB operand to locate program objects or load modules to which the executing load module refers.
- The external name for the loaded program's entry point.
- The name you want to assign to the loaded program.

This topic shows you how to use the basic functions of LOADGO. For a complete description of the LOADGO command, see [z/OS TSO/E Command Reference](#).

### Loading and Executing Programs with No Operands

To load and execute the source code in a data set or a group of data sets, issue the LOADGO command and specify the data set name. The rightmost qualifier of the data set name must be OBJ or LOAD. When loading and executing the code in a single data set, specify the data set name without parentheses.

For example, to load and execute the code in data set PAYROLL.LOAD, enter:

```
LOADGO PAYROLL.LOAD
```

When loading and executing the code in a group of data sets, specify the data set names in parentheses, separating each name with a comma. The names may be data set names, names of members of partitioned data sets, or both.

## LOADGO command

For example, to load and execute the code in data sets FIRST.OBJ, SECOND.OBJ and THIRD.LOAD, enter:

```
LOADGO (FIRST.OBJ,SECOND.OBJ,FIFTH.LOAD)
```

## Passing Parameters when Loading and Executing Programs

To pass parameters to a program when loading and executing it, specify the parameter enclosed in single quotes following the data set name field.

For example, to pass THE RAIN IN SPAIN as a parameter to the program in data set FIFTH.LOAD, enter:

```
LOADGO FIFTH.LOAD 'THE RAIN IN SPAIN'
```

## Requesting Output Listings when Loading and Executing Programs - the PRINT/NOPRINT and TERM/NOTERM Operands

To produce output listings and place them in a data set, use the PRINT operand with the data set name enclosed in parentheses. The NOPRINT operand, suppressing output listings, is the default. Note that the NOPRINT and MAP operands are mutually exclusive. The MAP operand, discussed below, puts data in the PRINT data set. Therefore, if you want the MAP information, you must also specify the PRINT operand with the LOADGO command.

For example, to send the output listings from the program in data set FIFTH.LOAD to data set OUT5.DATA, enter:

```
LOADGO FIFTH.LOAD PRINT(OUT5.DATA)
```

To produce output listings and send the output to your terminal, use the PRINT operand with an asterisk enclosed in parentheses.

For example, to send the output listings from the program in data set FIFTH.LOAD to your terminal, enter:

```
LOADGO FIFTH.LOAD PRINT(*)
```

All error messages are directed to your terminal as well as to the PRINT data set, as the TERM operand is a default with the LOADGO command. To direct all error messages only to the PRINT data set, not to your terminal, use the NOTERM operand.

For example, to direct all error messages only to the print data set OUT5.DATA, enter:

```
LOADGO FIFTH.LOAD PRINT(OUT5.DATA) NOTERM
```

## Resolving External References when Loading and Executing Programs - the CALL/ NOCALL and LIB Operands

To resolve external references, you must know in which data sets the code or data being referred to is kept. If you know the program object or load module library data set(s) name, use the LIB operand with the name enclosed in parentheses to tell the system where to look to resolve any external references.

For example, to search library data sets MYLIB, YOURLIB, and OURLIB, to resolve any external references when executing the program in FIFTH.LOAD, enter:

```
LOADGO FIFTH.LOAD LIB(MYLIB,YOURLIB,OURLIB)
```

The CALL operand is a default with the LOADGO command. The system will search for the data set(s) you specified on the LIB operand to locate the program objects or load modules to which the executing code refers.

Use the NOCALL operand following the LIB operand to prevent the system from searching the data set(s) you specified on the LIB operand.

For example, to suppress searching for program objects or load modules within data set MYLIB, YOURLIB, or OURLIB when executing the program in FIFTH.LOAD, enter:

```
LOADGO FIFTH.LOAD LIB(MYLIB,YOURLIB,OURLIB) NOCALL
```

To include a list of external names and their addresses in the PRINT data set, use the PRINT, LIB and MAP operands. The NOMAP operand is the default and does not include the MAP information in the PRINT data set.

For example, to resolve external references found in data set PROLIB, and list them in data set OUT5.DATA, enter:

```
LOADGO FIFTH.LOAD PRINT(OUT5.DATA) LIB(PROLIB) MAP
```

Note that MAP and NOPRINT are mutually exclusive operands.

## Specifying an Entry Point when Loading and Executing Programs - the EP Operand

To specify an external name for a program's entry point when loading and executing the program, use the EP operand with the entry point name enclosed in parentheses.

For example, to specify START as the external name for the entry point into the program in data set FIFTH.LOAD, enter:

```
LOADGO FIFTH.LOAD EP(START)
```

If the entry point of the loaded program is a program object or load module, you must specify this operand.

## Specifying Names when Loading and Executing Programs - the NAME Operand

To assign a name to a program in a data set, use the NAME operand followed by the name of the program.

For example, to assign the name PROG3 to the program in FIFTH.LOAD, enter:

```
LOADGO FIFTH.LOAD NAME(PROG3)
```

## CALL Command

---

Use the CALL command to load and execute a program that exists in executable (program object or load module) form. The program may be user-written or it may be owned by the system, for example, a compiler, sort, or utility program.

You can specify the name of the program (program object or load module) to be processed. It must be a member of a partitioned data set. If you do not specify a member name, member TEMPNAME is assumed. Also, you can pass parameters to the program.

This topic shows you how to use the basic functions of the CALL command. For a complete description of the CALL command, see [z/OS TSO/E Command Reference](#).

## Loading and Executing Load Modules

To load and execute a load module in a member of a partitioned data set, specify the name of the data set with the name of the member enclosed in parentheses.

## CALL command

For example, to load and execute the load module in member JOYCE of data set PUBS.LOAD, enter:

```
CALL PUBS(JOYCE)
```

If the partitioned data set does not conform to data set naming conventions, then you must specify the member name that contains the program you want to execute. If you specify a fully-qualified data set name, enclose it in single quotation marks in the following manner:

```
CALL 'D00ABC1.MYPROG.LOADM0D(DISCHARG)'
```

or

```
CALL 'SYS1.LINKLIB(IEUASM)'
```

If you do not enclose your data set name in quotes, a high-level *userid* is prefixed to the data set name and the low-level qualifier, LOAD, is attached as well.

For example, if USER1 accesses PUBS with the following:

```
CALL PUBS
```

the actual program accessed is in member TEMPNAME in USER1 . PUBS . LOAD.

## Passing Parameters when Loading and Executing Load Modules

To load and execute the load module in a partitioned data set and pass it parameters, specify the parameters enclosed in single quotation marks following the data set name.

For example, to pass PRANCE as a parameter to the load module in member UDOIT of data set DLW.LOAD, enter:

```
CALL DLW(UDOIT) 'PRANCE'
```

In the previous example, the CALL command translates the parameter list to uppercase characters. The ASIS operand of the CALL command prevents translation to uppercase. Use the ASIS operand to pass lowercase data to programs that accept lowercase characters in the parameter list.

For example, to pass LeaveAsis as a parameter to the load module in member NOTRANS of data set DLW.LOAD, enter:

```
CALL DLW(NOTRANS) 'LeaveAsis' ASIS
```

## Chapter 16. Testing a Program

This topic introduces the TSO/E TEST and TESTAUTH commands and describes how to test a program. It also discusses the terminology and concepts that you must understand to use the TEST and TESTAUTH commands. The tutorial topic gives a step-by-step explanation of how to use TEST and shows how TEST can help you determine the cause of a programming error. Because TEST and TESTAUTH support the same subcommands, the tutorial can help you learn about using TESTAUTH.

### The TEST and TESTAUTH Commands

The TEST and TESTAUTH commands permit you to test an assembler language program, including a command processor or application program, at your terminal. The TEST and TESTAUTH commands also allow you to test APPC/MVS transaction programs. Use the TEST command to test *unauthorized* programs; use the TESTAUTH command to test *authorized* programs.

#### The TEST Command

While you are executing an unauthorized program that you have written, you may encounter errors or abnormal terminations (abends). You can use the TEST command to help determine the cause of errors in a program that is currently executing. You can also use the TEST command to load and execute a program, and monitor the program's execution.

#### The TESTAUTH Command

You can use the TESTAUTH command to test an authorized program that is *not* currently executing. Unlike the TEST command, you cannot use TESTAUTH to test a currently executing program. However, the TESTAUTH command supports most of the same operands, subcommands and functions as the TEST command.

#### Using TEST or TESTAUTH

Test a program by issuing either the TEST or TESTAUTH command. The TEST command issues the TEST mode message to let you know that the system is waiting for you to enter a subcommand. Similarly, the TESTAUTH command issues the TESTAUTH mode message. Then use the various subcommands to perform the following basic functions:

- Supply test data that you want to pass to the program.
- Execute the program from its starting address or from any address within the program.
- Step through sections of the program, checking each instruction for proper execution.
- Display selected areas of the program as they currently appear in virtual storage, or display the contents of any of the registers.
- Interrupt the program at specified locations. After you have interrupted the program, you can display areas of the program or any of the registers, or you can issue other subcommands to be executed before returning control to the program being tested. A location in a program where you interrupt execution is called a *breakpoint*. Breakpoints that are specified for programs that are not yet in virtual storage are called *deferred breakpoints*. You can establish deferred breakpoints for programs that will be brought into virtual storage during execution of the program being tested.

The following restrictions apply when specifying breakpoints:

- Do not insert breakpoints into the TSO/E service routines or into any of the TEST or TESTAUTH load modules.
- The TESTAUTH command does not support breakpoints in storage that has a protection key other than 8.

## When to use the TEST and TESTAUTH commands

- When running in supervisor state or in a PSW protection key other than 8, the TEST command does not honor breakpoints in any section of your program.
- Change the contents of specified program locations in virtual storage or the contents of specific registers. You do this with the assignment function.

**Note:** The TESTAUTH command does not allow you to modify the contents of storage that has a protection key other than 8.

In addition to these basic debugging functions, the TEST and TESTAUTH command processors provide other functions, such as listing data extent blocks (DEBs), data control blocks (DCBs), task control blocks (TCBs), program status words (PSWs), and providing a virtual storage map of the program being tested.

The discussion of the TEST and TESTAUTH commands in this book shows you how to use these basic functions. For a complete description of the syntax and functions of the subcommands, see [z/OS TSO/E Command Reference](#). For more information on the TESTAUTH command, see [z/OS TSO/E System Programming Command Reference](#).

## When to Use the TEST and TESTAUTH Commands

---

You can use the TEST command to:

- Test a currently executing, unauthorized program.
- Test an unauthorized program not currently executing.

You might want to test an executing program because it terminated abnormally or because you want to check the current environment to see that the program is executing properly.

You can use the TESTAUTH command to test an authorized program that is *not* currently executing.

### Testing a Currently Executing Program

If an unauthorized program terminates abnormally, you receive a diagnostic message from the terminal monitor program (TMP) followed by a READY message. If you respond to the diagnostic message with anything other than TEST, a question mark (?), or TIME, the TMP terminates your program. If you issue the TEST command without a program name, the currently active program remains in storage when the TEST command processor gets control, and you can use the TEST subcommands to debug the defective program.

You can enter both the ? and the TIME command before issuing the TEST command to debug an abnormally terminating program. If you want a dump, enter a null line instead of issuing the TEST command. If a SYSABEND, SYSMDUMP, or SYSUDUMP file has already been allocated, the null line results in a dump being printed.

If you want to examine the current environment of an executing program that is not terminating abnormally, enter a single attention interruption. The currently active program remains attached and the TMP responds to your interruption by issuing a READY message. When you issue the TEST command without a program name, the currently active program remains in storage under the control of the TEST command processor. You can then use the TEST subcommands to examine the current environment.

In the case of either an abend or an attention interruption, you should *not* enter a program name following the TEST command. If you do, you lose the current in-storage copy of the program because TEST loads a copy of the program you specified instead. Even if you specify the name of the currently active program, a new copy is loaded and the current one is lost.

### Testing a program not currently executing

To test a program not currently executing, specify on the TEST or TESTAUTH command the data set name containing the program to be executed and any other applicable operands.

You can load and execute a program under the control of the TEST command processor if it is either:

- A link-edited member of a partitioned data set or extended partitioned data set (PDSE).



- An object module in a sequential or partitioned data set or PDSE.

You can load and execute a program under the control of the TESTAUTH command processor if it is a link-edited member of an APF-authorized library.

Issue the TEST or TESTAUTH command followed by the program name and the operands of the command that either define the program or are necessary to its operation. For example:

- For the TEST command, the keyword LOAD or OBJECT depending on whether the program is a load or an object module. The TESTAUTH command does not support the OBJECT keyword. LOAD is the default.
- The keyword CP, TP, or NOCP, depending on whether the program to be tested is a command processor, an APPC/MVS transaction program, or is another type of program that is not a command processor or a transaction program. NOCP is the default.

**Note:** You only need to specify the TP keyword if you are testing an inbound APPC/MVS transaction program (see [“Testing an APPC/MVS Transaction Program” on page 81](#)). You can test outbound transaction programs as ordinary programs.

- Additional parameters necessary for the program being tested.

If the program you are testing is a command processor, specify the keyword CP. The CP keyword causes the test routine to create a command processor parameter list (CPPL), and place its address into register 1 before loading the program. If you do not explicitly specify the CP operand, any parameters that you specify in the TEST or TESTAUTH command are passed to the named program as a standard operating system parameter list. That is, when the program under TEST or TESTAUTH receives control, register 1 contains a pointer to a list of addresses that point to the parameters.

To test an inbound APPC/MVS transaction program, specify the TP operand.

- Use the LU or BASELU keyword to specify the LU on which to test the transaction program. These operands are valid only when you use the TP keyword operand. BASELU is the default.
- Use the keyword KEEPTP to specify that TEST or TESTAUTH should not clean up the transaction program and its conversations when TEST ends. If you do not specify this keyword, the TSO/E TEST command cleans up the transaction program and its conversations.

## Testing an APPC/MVS Transaction Program

The following example outlines the required steps for testing an APPC/MVS transaction program with the TSO/E TEST command:

```
READY
(1) test (myprog) tp('MAIL') kepttp
(2) IKJ57522I YOU CAN ALLOCATE THE TP NOW
    +++ the user starts a program that allocates the TP to be tested +++
(3) TEST
    +++ the user can now test the TP as if it is an ordinary program +++
(4) TEST
(5) end
(6) READY
```

1. *Prefix*.LOAD(myprog) contains the load module for the transaction program to be tested. MAIL is the transaction program name under which the load module is to be tested. The inbound allocate request will try to allocate MAIL.
2. Wait for TSO/E TEST to prompt you to allocate the transaction program to be tested. The message IKJ57522I indicates that it is your turn to start a program that allocates an APPC/MVS conversation with the transaction program to be tested.

## Examples of issuing the TEST and TESTAUTH commands

3. TEST displays a TEST mode message, indicating that it is your turn to enter TEST subcommands to control TEST's processing.
4. TEST returns control to the terminal with another mode message.
5. To terminate TEST processing, use the END subcommand.
6. TEST returns to READY mode.

Because the LU keyword is not specified in this example, TSO/E TEST uses the base LU for testing (BASELU is the default keyword). Also, the transaction program and its remaining conversations are not cleaned up by the TEST command because the KEEPTP keyword is specified.

## Examples of Issuing the TEST and TESTAUTH Commands

---

The following examples show you how to invoke a program or a command processor for testing:

### Example 1

**Operation:** Enter TEST mode after experiencing either an abnormal termination of an unauthorized program or an attention interruption.

**Known:**

- Either you have received a message saying that your foreground program has terminated abnormally, or you have pressed the attention interrupt key while your program was executing. In either case, you would like to begin debugging your program.

```
test
```

### Example 2

**Operation:** Invoke an unauthorized program for testing.

**Known:**

- The name of the data set that contains the program: TLC55.PAYER.LOAD(THRUST)
- The program is a load module and is not a command processor.
- The prefix in the user's profile is TLC55.
- The parameters to be passed: 2048, 80

```
test payer(thrust) '2048,80'
```

or

```
test payer.load(thrust) '2048,80'
```

### Example 3

**Operation:** Invoke an unauthorized program for testing.

**Known:**

- The name of the data set that contains the program: TLC55.PAYLOAD.OBJ
- The prefix in the user's profile is TLC55.
- The program is an object module and is not a command processor.

```
test payload object
```

### Example 4

**Operation:** Test an unauthorized command processor.

**Known:**

- The name of the data set containing the command processor: TLC55.CMDS.LOAD(OUTPUT)

```
test cmds(output) cp
```

or

```
test cmds.load(output) cp
```

**Note:** You will be prompted to enter a command for the command processor.

**Example 5**

**Operation:** Invoke an unauthorized command processor for testing.

**Known:**

- The name of the data set containing the command processor is TLC55.LOAD(OUTPUT).
- The prefix in the user's profile is TLC55.

```
test (output) cp
```

**Example 6**

**Operation:** Invoke an authorized program for testing.

**Known:**

- The name of the data set containing the program: 'SYS1.LINKLIB(AUTHPGM)'
- The program is not a command processor.

```
testauth 'sys1.linklib(authpgm)'
```

**Example 7**

**Operation:** Test an authorized command processor.

**Known:**

- The name of the data set containing the command processor: 'SYS1.LINKLIB(AUTHCMD)'

```
testauth 'sys1.linklib(authcmd)' cp
```

**Example 8**

**Operation:** Test an unauthorized APPC/MVS transaction program.

**Known:**

- The name of the data set containing the transaction program. USER.APPC.LOAD(TESTTP)

```
test 'user.appc.load(testtp)' tp('TESTTP')
```

**Example 9**

**Operation:** Test an unauthorized APPC/MVS transaction program and do not clean up the transaction program and its conversations when TEST ends.

**Known:**

- The name of the data set containing the transaction program. USER.APPC.LOAD(TESTTP)

```
test 'user.appc.load(testtp)' tp('TESTTP') keep tp
```

## Example 10

**Operation:** Test an authorized APPC/MVS transaction program and specify which LU is to be used.

**Known:**

- The name of the data set containing the transaction program. USER.APPC.LOAD(TESTTP)
- VTAMNODE.LU1 is the LU on which the transaction program is to be tested.

```
testauth 'user.appc.load(testtp)' tp('TESTTP') lu('VTAMNODE.LU1')
```

## TEST and TESTAUTH Subcommands

The TEST command issues the TEST mode message to let you know that the system is waiting for you to enter a subcommand. Similarly, the TESTAUTH command issues the TESTAUTH mode message. The subcommands of the TEST and TESTAUTH commands are shown in Table 13 on page 84. The tutorial in the next topic shows you how to use many of these subcommands to help determine the cause of errors and to monitor the execution of your program. For a complete description of the syntax and function of each subcommand, and for a list of the TSO/E commands that you can use under TEST and TESTAUTH, see [z/OS TSO/E Command Reference](#).

Table 13: The TEST and TESTAUTH Subcommands	
Subcommand	Function
AND	Performs a logical AND operation on data in two locations, placing the results in the second location specified.
ASSIGNMENT OF VALUES(=)	Modifies values in virtual storage and in registers.
AT	Establishes breakpoints at specified locations.
CALL	Initializes registers and initiates processing of the program at a specified address using the standard subroutine linkage.
COPY	Moves data.
DELETE	Deletes a load module from virtual storage.
DROP	Removes symbols established by the EQUATE command from the symbol table of the module being tested.
END	Terminates all operations of the TEST or TESTAUTH command and the program being tested.
EQUATE	Adds a symbol to the symbol table and assigns attributes and a location to that symbol.
FREEMAIN	Frees a specified number of bytes of virtual storage.
GETMAIN	Acquires a specified number of bytes of virtual storage for use by the program being processed.
GO	Restarts the program at the point of interruption or at a specified address.
HELP	Lists the subcommands of TEST and TESTAUTH and explains their function, syntax, and operands.
LIST	Displays the contents of a virtual storage area or registers.
LISTDCB	Lists the contents of a data control block (DCB). You must specify the address of the DCB.

Table 13: The TEST and TESTAUTH Subcommands (continued)

Subcommand	Function
LISTDEB	Lists the contents of a data extent block (DEB). You must specify the address of the DEB.
LISTMAP	Displays a map of the user's virtual storage.
LISTPSW	Displays a program status word (PSW).
LISTTCB	Lists the contents of the current task control block (TCB). You can specify the address of another TCB.
LISTVP	Lists the vector section size and the partial sum number.
LISTVSR	Displays the vector status register (VSR).
LOAD	Loads a program into virtual storage for execution. An authorized program loaded by the TESTAUTH command must reside in an APF-authorized library.
OFF	Removes breakpoints.
OR	Performs a logical OR operation on data in two locations, placing the results in the second location specified.
QUALIFY	Establishes the starting or base location for resolving symbolic or relative addresses; resolves identical external symbols within a load module.
RUN	Terminates TEST or TESTAUTH and completes execution of the program.
SETVSR	Changes the vector mask register control mode. Updates the vector count (VCT), the vector interruption index (VIX), and the vector in-use bits (VIU).
WHERE	Displays the virtual address of a symbol or entry point, or the address of the next executable instruction. WHERE can also be used to display the module and CSECT name and the displacement into the CSECT corresponding to an address.

## Addressing Conventions Associated with TEST and TESTAUTH

Many of the tasks you can perform with TEST and TESTAUTH involve using subcommands that require you to specify an address. For example, to display the contents of a storage location, you must indicate the address of the area to be displayed. An address used as an operand for a subcommand must be one of the following types:

- Absolute address
- Relative address
- Symbolic address
- Module name and entry name (separated by a period)
- Qualified address
- General register
- Floating-point register
- Vector register
- Vector mask register
- Access register
- Indirect address
- Address expression

These address types are described in the following topics.

### Absolute Address

A virtual storage address. An absolute address is 1 to 8 hexadecimal digits followed by a period and not exceeding X'7FFFFFFF'. For example,

```
BC3D60.
```

is an absolute address.

### Relative Address

A one-to eight-digit hexadecimal number preceded by a plus sign (+). A relative address specifies an offset from the currently qualified virtual storage address. For example,

```
+A0
```

is a relative address. See the discussion on qualified addresses that follows.

### Symbolic Address

One to eight alphameric characters, the first of which is an alphabetic character. A symbolic address corresponds to a symbol in a program or a symbol defined by the EQUATE subcommand. Qualified symbolic addressing is discussed below. For a detailed description on the use of symbols, see [“Restrictions on the Use of Symbols” on page 90.](#)

### [Module-Name].Entry-Name

A name within a module capable of being externally referenced, preceded by a period (.), and optionally preceded by a name by which the module is known. An entry name is the symbolic address of an entry point into the module; for example, a CSECT name. A module name can be the name or alias of a load module or the name of an object module. Module or entry names can be any combination of up to eight alphameric characters, the first of which is alphabetic or national.

### Qualified Addresses

You can qualify symbolic or relative addresses to indicate they apply to a particular module and CSECT. To do this, you must precede the address by the name of the load or object module and the name of the CSECT. The qualified address must be in the form:

```
modulename.csect.address
```

If the address is to apply to the current module, you only need to specify the CSECT name in the following form:

```
csect.address
```

If the address is to apply to the current CSECT within the current module, only the address is necessary; you do not need to qualify the address. The current module and CSECT is initially set to the program being tested. This setting is automatically changed each time a module under a different request block is invoked. This is referred to as *automatic qualification*. Automatic qualification occurs when a module is invoked by ATTACH, XCTL, SYNCH, or LINK. It does *not* occur when a module is loaded, called, or branched to.

The module or CSECT used in determining a base location for resolving symbolic and relative addresses can also be changed by using the QUALIFY subcommand.

For example, if the name of the module is OUTPUT, the CSECT is TAXES, and the symbolic address is YEAR77, you would specify either:

```
output.taxes.year77
```

or

```
.taxes.year77
```

If the current module is OUTPUT. You would specify:

```
year77
```

If the module name and CSECT name are the same as above and the address to be qualified is the relative address +4A, you would specify:

```
output.taxes.+4A
```

## General Registers

You can refer to a general register using the AND, OR, assignment-of-value, COPY, or LIST subcommands by specifying a decimal integer followed by an R. The decimal integer indicates the number of the register and must be in the range 0 through 15. Other references to the general registers imply indirect addressing.

If your program issues the STIMER macro or involves asynchronous interruptions, the contents of your registers may be changed by interruptions even though you are in *subcommand* mode and your program does not get control.

## Floating-Point Registers

You can refer to a floating-point register using the LIST or assignment-of-value subcommand by specifying a decimal integer followed by an E or D. The decimal integer indicates the number of the register and *must be* a zero, two, four, or six. An E indicates a floating-point register with single precision. A D indicates a floating-point register with double precision. You *must not* use floating-point registers for indirect addressing or in expressions.

## Vector Registers

You can refer to a vector register using the LIST or assignment-of-value subcommand. You cannot use vector registers for indirect addressing or in expressions. Specify a vector register address by using the following format:

```
register-number { V } { W } (element-number)
```

### **register-number**

consists of a decimal integer in the range 0 through 15 if V is specified. If W is specified, the register number must be an even decimal integer in the range 0 through 14.

### **V**

indicates single precision. V can be entered in either uppercase or lowercase.

### **W**

indicates double precision. W can be entered in either uppercase or lowercase.

### **element-number**

consists of a decimal integer in the range 0 through one less than the section size, or an asterisk, (\*). Asterisk indicates that all elements of the vector register are considered.

The section size, which is the number of elements in a vector register, is dependent upon the model of the CPU that has the vector facility installed. See *System/370 Vector Operations* for information on the vector facility.

The list below shows several examples of specifying vector registers:

### **1V(\*)**

Specifies the entire contents of vector register 1 in single precision.

**1V(4)**

Specifies element 4 of vector register 1 in single precision.

**0W(1)**

Specifies element 1 of vector registers 0 and 1 in double precision.

**Vector Mask Register**

You can refer to the vector mask register using the LIST or assignment-of-value subcommand. A vector mask register address consists of the decimal integer 0 followed by an M. You cannot use the vector mask register for indirect addressing or in expressions.

**Access Registers**

You can refer to an access register using the LIST, COPY, or assignment-of-value subcommand by specifying a decimal integer followed by an A. The decimal integer indicates the number of the register and must be in the range 0-15. You cannot use access registers for indirect addressing or in expressions.

**Indirect Address**

An indirect address is an absolute, relative, or symbolic address, (or a general register containing an address) of a location that contains another address. An indirect address *must* be followed by one or more indirection symbols to indicate a corresponding number of levels of indirect addressing.

The indirection symbols are:

- The percent sign (%), indicating that the low-order three bytes of the address are used.
- The question mark (?), indicating that all 31 bits are used for the address.


To use a general register as an indirect address, specify a decimal integer (0 through 15) followed by an R and a percent sign, or an R and a question mark. For example, if you want to refer to data whose address is located in register 7, you would specify:

```
7R%
```


**Example:** Use of a relative address to form an indirect address.

**Address:** +A% (One level of indirect addressing)

Address: +A% (One level of indirect addressing)



Address: +A?



**Example:** Comparison of use of % and ?




Address	Data
X	0100A080
0000A080	AAAAAAAA
0100A080	BBBBBBBB

Subcommand	Data Displayed
LIST X	0100A080
LIST X%	AAAAAAAA
LIST X?	BBBBBBBB

**Example:** Indirect addressing using a combination of indirection symbols.

**Address expression:** +A%??% (Four levels of indirect addressing)



## Address Expression

An address followed by any number of expression values. You can specify the address as:

- An absolute address
- A relative address (unqualified, partially or fully-qualified)
- A symbolic address (unqualified, partially or fully-qualified)
- An indirect address

An expression value consists of a plus or minus displacement value expressed as either 1 to 8 hexadecimal digits or 1 to 10 decimal digits from an address in virtual storage. Following are two examples of address expressions:

**Decimal Example:** address+14n specifies the location that is 14 bytes past that designated by “address.”

**Hexadecimal Example:** address+14 specifies the location that is 20 decimal bytes past that designated by “address.”

## Restrictions on the use of symbols


Decimal displacement (either plus or minus) is indicated by the n following the numeric offset. You can indicate up to 256 levels of indirect addressing by following the initial indirect address with a corresponding number indirection symbols (% or ?). An address expression is specified in the following format:

```
address { - } value [ ? ] [ { - } value [ ? ] ]  
          { + } value [ % .. ] [ { + } value [ % .. ] ] ...
```

You can use any combination of percent signs and question marks after the value.

**Example:** Address expression with hexadecimal displacement using a combination of indirection symbols.

**Address expression:** 7R?%+C%??%



When processing an address expression, TEST and TESTAUTH check the high-order bit of the result of each addition or subtraction. If the bit is on, indicating a negative value or overflow condition, the address is rejected.

## Restrictions on the Use of Symbols

The TEST and TESTAUTH command processors can resolve external and internal symbolic addresses, only if those addresses are available. Within certain limitations, symbolic addresses are available for both object modules (processed by the loader) and load modules (fetched by contents supervision). To ensure availability of symbols, use the EQUATE subcommand to define the symbols you intend to use. [“Using Additional Features of TEST”](#) on page 114 shows you how to do this.

### External Symbols

You can access external symbols, such as CSECT names, for a program module, if the program was brought into main storage by the TEST or TESTAUTH command or one of its subtasks. This is the case for the program being tested, any program brought into storage through the tested program, and any program loaded by the LOAD subcommand.

External symbols for CSECT names that are in object modules are available only if the loader had enough main storage to build composite external symbol table dictionary (CESD) entries.

## Internal Symbols

Internal symbols for load modules can be resolved if the CSECT containing the symbol was assembled with the TEST parameter, the module was link-edited with the TEST parameter, and the program was brought into storage by the TEST or TESTAUTH command or one of its subtasks as previously explained. Names on EQU, ORG, LTORG, CNOP, and DSECT statements *cannot* be resolved.

You cannot access internal symbols for object modules.

## Addressing Considerations

If the necessary conditions for symbol processing are not met, you can use absolute, relative, or indirect addressing, or you can define symbols with the EQUATE subcommand.

Symbols within DSECTs are available only if the DSECT name has been defined with the EQUATE subcommand.

For example, if NAME is a symbol in a DSECT named DATATBL, then to access the data associated with NAME, you would first have to determine the address to be used as a base address for the DSECT. (This is the address in the register on the assembler USING instruction.) If the address is in register 7, you can enter:

```
equate datatbl 7r%
```

This establishes addressability to the DSECT, allowing the symbol NAME and all other symbols in the DSECT to be accessed using the symbol.

TEST and TESTAUTH can access symbols and process CSECT names (to qualify addresses and satisfy deferred breakpoints) for a module loaded from a data set in LNKLIST concatenation, provided that the module was both assembled and link-edited with the TEST option, and the data set involved is not READ-protected. Symbols and CSECT names cannot be processed for a module accessed from LPA.

## Examples of Valid Addresses in TEST and TESTAUTH Subcommands

The following are examples that can be used with subcommands. In these addresses, PROFIT is a module name, SALES is a CSECT name, and NAMES is a symbol.

### Address:

#### Type of Address:

#### A23C40.

Absolute

#### +E4

Relative

#### 5R%

24-bit indirect

#### 5R?

31-bit indirect

#### NAMES

Symbol within program

#### .SALES.+26

Partially-qualified relative

#### 14R%+28

Expression

#### PROFIT.SALES

Module and entry name

**+16+10n**

Expression

**.SALES.NAMES**

Partially-qualified symbol

**PROFIT.SALES.NAMES+8n**

Expression

**DATA+10**

Expression

**.SALES**

Entry name

**PROFIT.SALES.NAMES**

Fully-qualified symbol

**6R%+4%+12n%%**

Expression

**PROFIT.SALES.+C0**

Fully-qualified relative

## Programming Considerations for Using TEST and TESTAUTH

---

When you use the TEST or TESTAUTH command, consider the environment in which your program is running. The topics that follow describe programming considerations for the following:

- Using 31-bit addressing
- Using the virtual fetch services
- Executing in a cross-memory environment
- Using the vector facility
- Using extended addressability
- Testing APPC/MVS transaction programs
- Evaluating a program's environment after testing

### Considerations for 31-Bit addressing

- All subcommands that accept addresses can process addresses above 16 MB, regardless of the current addressing mode of the program.
- You can use the 31-bit indirection symbol (?) on any subcommands to reference data pointed to by 31-bit addresses.
- When TEST or TESTAUTH loads and executes a program, it uses the AMODE and RMODE characteristics to determine the addressing mode at entry, as well as whether the tested program is loaded above or below 16 MB.
- The AMODE operand on the CALL, GO, and RUN subcommands can change the addressing mode of the program being tested.
- The loader, which TEST and TESTAUTH invoke when testing an object module, loads the module above or below 16 MB based on the RMODE characteristics of the module's CSECTs. If the first CSECT is RMODE(ANY) and any other CSECTs are RMODE(24), the loader loads the module below 16 MB in storage and issues a warning message.
- Input passed in register 1 to the program being tested is below 16 MB in storage. If you invoke the TEST or TESTAUTH command with the CP operand, register 1 contains the address of the command processor parameter list (CPPL). Otherwise, register 1 contains the address of the input parameter list.
- The CALL subcommand places the return address of the tested program in register 14. The high-order bit of register 14 is set to reflect the addressing mode of the tested program.

- If the called program should not be invoked in the current addressing mode, specify AMODE on the CALL statement. When control is returned, verify that the addressing mode is appropriate before continuing execution.

## Considerations for Using the Virtual Fetch Services

- External symbols are not available for a program fetch. For information on addressing considerations, see [“Restrictions on the Use of Symbols”](#) on page 90.
- Do not establish deferred breakpoints for a program managed by virtual fetch because they are ignored.
- If you are testing program A, which invokes program B using the virtual fetch services, you cannot use TEST or TESTAUTH subcommands to stop execution of program B.
- If, while testing program A, you want to debug program B, you can use the following method. Instead of allowing a virtual fetch GET request to pass control to program B, load and call program B using TEST or TESTAUTH subcommands.
  - Use the AT subcommand to establish a breakpoint immediately before the virtual fetch GET request in program A.
  - When you reach the breakpoint, use the LOAD subcommand to load a different copy of program B.
  - You can then establish breakpoints using the AT subcommand at any points in this copy of program B.
  - Use the CALL subcommand to execute program B. Specify an address on the RETURN parameter to bypass the virtual fetch GET request in program A.

**Note:** You cannot use the facilities of TEST or TESTAUTH to debug a program's interface with virtual fetch. For a description of the virtual fetch services, see [z/OS MVS Using the Subsystem Interface](#).

## Considerations for a Cross-Memory Environment

- If an attention interruption occurs while the program being tested is executing in cross-memory mode, and you enter anything other than a null line, the cross-memory environment is terminated and a message is displayed.
- If TEST or TESTAUTH is used with cross-memory applications, access to storage by TEST or TESTAUTH subcommands is restricted to the home address space.
- If an abnormal termination (abend) occurs while a cross-memory application is executing outside the home address space, TEST and TESTAUTH do not preserve the cross-memory environment. The registers and PSW at the time of the abend and the abend code from the error message are the only debugging information available for a cross-memory abend.
- TEST provides only limited testing for programs that execute in cross-memory mode. The reason is that code running in cross-memory mode cannot issue any SVCs (except ABEND). Any system service that depends on SVCs is unavailable in cross-memory mode.

If a breakpoint is set, TEST places a SVC in the code being tested. When the code being tested reaches the breakpoint, the SVC returns control to TEST alerting it that a breakpoint has been hit. If the code under test is in cross-memory mode this SVC cannot be issued and an abnormal termination occurs.

Therefore, do not set breakpoints in code that will be running in cross-memory mode.

Breakpoints set on instructions that perform address space switching are intercepted by SVCs inserted by TEST.

## Considerations for the Vector Facility

The TEST and TESTAUTH commands support the use of 16 vector registers, the vector status register, and the vector mask register. Each of the 16 vector registers contains a number of four-byte elements that are dependent on the model of the CPU. The vector status register has special information about the vector registers being processed.

You can use the TEST and TESTAUTH commands to display and modify the contents of the 16 vector registers, display the vector status register, set breakpoints at the vector opcodes, display the vector

opcodes in their assembler language format, view the partial sum number, view the vector section size, and set fields in the vector status register.

- Use the LIST subcommand to display the contents of the 16 vector registers in one of the following formats:

- A single element
- Multiple elements
- All elements at once

You can list registers in single precision floating point, fixed- point fullword binary or hexadecimal format. The even numbered vector registers can also be displayed in double precision floating point format.

- You can use the LIST subcommand to display the vector mask register. TEST and TESTAUTH display the vector mask register in hexadecimal or binary format. The length of the data displayed depends on the model of the CPU that has the vector facility installed.
- Use the LISTVSR subcommand to display the vector status register.
- You can use the assignment function to modify the 16 vector registers in the same format as you list them, that is, one at a time, some, or all at once. You can use the assignment function to modify the vector mask register. The value you assign to the vector mask register must be binary or hexadecimal.
- You can use the LISTVP subcommand to display the partial sum number and vector section size.
- You can use the SETVSR subcommand to set fields in the vector status register. You can change the vector mask register control mode, update vector count (VCT), update vector interruption index (VIX), and update vector in-use bits (VIU).

For examples showing how to display and manipulate vector registers and elements, see [“Testing Programs That Use the Vector Facility”](#) on page 121.

### Considerations for Extended Addressing

The TEST and TESTAUTH commands allow you to test programs that use extended addressing. You can use the TEST and TESTAUTH commands to display and modify the contents of the 16 access registers, set breakpoints at the opcodes that support access registers, and display the opcodes in their assembler language format. However, you cannot set breakpoints for the program return (PR) instruction.

- Use the LIST subcommand to display:
  - The contents of access registers used to reference data in alternate address/data spaces. You can display the contents of the 16 access registers in either binary, hexadecimal or decimal format.
  - Data contained in alternate address/data spaces.
- Use the assignment function to modify the contents of the 16 access registers and of storage in alternate address/data spaces.
- Use the COPY subcommand to copy data to an alternate address/data space or from an alternate address/data space.
- Use the ASCMODE operand on the CALL, GO and RUN subcommands to change the address space control (ASC) mode for the executing program.

**Note:** You can set breakpoints at addresses in the primary address space only.

For examples showing how to display and manipulate access registers, see [“Testing Programs That Use Extended Addressing”](#) on page 123.

### Considerations for Testing Inbound APPC/MVS Transaction Programs

You can use the TEST and TESTAUTH commands to test APPC/MVS transaction programs. You can use the commands with inbound transaction programs—those that are initiated in response to inbound conversation requests from their partner transaction programs. When testing an APPC/MVS transaction program:

- There must not be a transaction program existing in the TSO/E user's address space when the TSO/E TEST or TESTAUTH command is invoked to test an APPC/MVS transaction program. You should log on with a logon procedure that does not allocate APPC/MVS conversations if an APPC/MVS transaction program is to be tested. After TSO/E TEST has been invoked with the TP keyword, you can allocate DFM data sets. However, if you want to invoke TEST again, you may have to log off and then log on again.
- You cannot use the TSO/E TEST or the TESTAUTH command to completely test multi-trans (multiple transaction) transaction programs. You can, however, use TSO/E TEST to partially test an APPC/MVS multi-trans transaction program up to the point when the transaction program attempts to get the next transaction.
- The user-level transaction program profile for the LUs that are to be used for transaction program testing must be defined at installation time. To define a user-level transaction program profile, the LUADD statement in PARMLIB member APPCPMxx must include the TPLEVEL(USER) keyword.
- If you press the attention key while waiting for the inbound allocate request, and enter anything other than a null line, TSO/E cancels the test request.
- If you press the attention key twice to end the TSO/E TEST or TESTAUTH command, and enter anything other than a null line, TSO/E cancels the command. The TSO/E TEST or TESTAUTH command cleans up the transaction program you are testing unless the KEEPTP keyword is specified.

## Considerations for a Tested Program's Environment

After the TEST or TESTAUTH command finishes processing a program, the program's environment has the following characteristics:

- The ASC mode is primary
- The primary, secondary, and home address spaces are equal
- The primary, secondary, and home address spaces are the same as when the program was invoked

If the program you are testing ends abnormally, the environment of the tested program might not be identical to the environment that it had prior to its ending. The environment of the tested program might have one or more of the following characteristics when it ends:

- The ASC mode was not primary
- The primary, secondary, and home address spaces were not equal
- The primary, secondary, and home address spaces were not the same as when the program was invoked

You can use the assignment functions of the TEST command to correct the ASC mode and address spaces. You can then correct the problem that caused the abend in the program and continue testing.

Refer to [z/OS TSO/E Command Reference](#) for additional information about the assignment functions of the TEST command.

If you cannot correct the environment of the tested program, you might be unable to test the remainder of the program. (For example, you cannot correct the environment of a tested program if that program was running in cross-memory mode.) You must end your test session, correct the abend, and then test the program again.





## Chapter 17. A Tutorial Using the TEST Command

This chapter is presented in tutorial form, and is intended for TSO/E users who have never used the TEST command to test a program. Before reading this chapter, you must be familiar with the concepts and terminology presented in [Chapter 16, “Testing a Program,”](#) on page 79.

This tutorial describes how to use TEST subcommands to test and debug a program. If you are an authorized user, you can use the TESTAUTH command to test authorized programs. Because TESTAUTH supports the same subcommands as TEST, you can use this tutorial to learn about using TESTAUTH.

This tutorial describes how to use the following subcommands:

Task	Subcommands
View storage and registers	LIST, LISTMAP, LISTPSW, LISTDCB, LISTDEB, LISTTCB, LISTVP, LISTVSR
Find addresses	WHERE
Control breakpoints	AT, OFF
Alter storage and registers	COPY, assignment of values function (=)
Alter vector registers	SETVSR
Add and alter symbols	EQUATE, DROP
Modify a base address	QUALIFY
Control program execution	GO, CALL, RUN
Obtain and free additional storage	GETMAIN, FREEMAIN
Obtain and free other programs	LOAD, DELETE
Obtain help information	HELP
Terminate a TEST session	END, RUN

The TEST subcommands use the address types described in [“Addressing Conventions Associated with TEST and TESTAUTH”](#) on page 85. This tutorial shows you how to use the following address forms and their notation:

Table 14: Address Forms Supported by TEST	
Address Form	Notation
Single address	A single address.
Range of addresses	Two addresses separated by a colon.
List of addresses	Addresses enclosed in parentheses, and separated by blanks or commas.

The tutorial is presented in the following sequence:

1. [“Preparing to Use TEST”](#) on page 98 describes how to assemble and link-edit your program, and how to invoke TEST, run the program, and terminate the TEST session.
2. [“Viewing a Program in Storage”](#) on page 100 shows several examples using the LIST subcommand to view registers and storage. It also shows how to use the different forms and types of addresses TEST supports.
3. [“Monitoring and Controlling Program Execution”](#) on page 108 shows you how to use breakpoints with the AT, GO, and OFF subcommands.

4. [“Altering Storage and Registers”](#) on page 111 illustrates the use of the assignment function and the COPY subcommand for altering storage to set up test cases.
5. [“Using Additional Features of TEST”](#) on page 114 shows you how to use the specialized LIST subcommands: LISTMAP, LISTPSW, LISTDCB, LISTDEB, and LISTTCB. Also, it further demonstrates the use of the WHERE subcommand, and introduces the QUALIFY and EQUATE subcommands.

[“More TEST Subcommands”](#) on page 120 follows the tutorial and describes the uses of the GETMAIN, FREEMAIN, LOAD, DELETE, and CALL subcommands. [“Testing Programs That Use the Vector Facility”](#) on page 121 discusses how to test programs that use vector registers and elements.

## How to Use This Tutorial

---

This tutorial is presented in a two-page format. The left-hand pages contain sample terminal sessions. Information that you enter at the terminal is in lower case; the responses from TSO/E are in upper case. The right-hand pages contain explanations of the sample terminal sessions.

To use this tutorial at your terminal, enter the commands shown on the sample terminal sessions (left-hand pages) and, at the same time, read the corresponding explanations on the right-hand pages. Numbers provide a cross-reference from the sample terminal sessions to the explanations.

You will need copies of the sample programs that are supplied in SYS1.SAMPLIB, along with their corresponding object files. The table below shows the members of SYS1.SAMPLIB that contain the source and object data used in this tutorial.

Source Member	Object Member
IKJSAMP1	IKJOB1
IKJSAMP2	IKJOB2

To use this tutorial at your terminal, create a data set called *'prefix.SAMPLE1.ASM'* that is a sequential data set of one track, with DCB characteristics of RECFM=FB, LRECL=80, BLKSIZE=3120. Copy the source code from 'SYS1.SAMPLIB(IKJSAMP1)' into your data set.

**Note:** The source code and the assembler listings for the sample programs used in this tutorial are also shown in [“Example programs for the TEST tutorial”](#) on page 125.

This tutorial guides you through:

- Using the subcommands of TEST to:
  - Change the contents of general purpose registers.
  - Control the execution of a program including the re-execution of instructions.
  - Change the contents of main storage variables and buffers.
  - Assign names to main storage locations.
  - Obtain and free additional main storage, as needed.
  - Locate the real address of your program.
  - List the PSW.
- Using the various methods of addressing main storage under TEST.

## Preparing to Use TEST

---

To test your program, it must be in object module or load module form. Therefore, you must first perform an assembly or an assembly and link-edit on your program. You can do this with a batch job, or by issuing TSO/E commands in the foreground. This tutorial uses foreground commands.

```

(1) READY

(2) asm sample1 test

(3) ASSEMBLER (XF) DONE
    NO STATEMENTS FLAGGED IN THIS ASSEMBLY
    HIGHEST SEVERITY WAS      0
    OPTIONS FOR THIS ASSEMBLY
      ALIGN, ALOGIC, BUFSIZE(STD), NODECK, NOESD, FLAG(0), LINECOUNT(55),
      NOLIST, NOMCALL, YFLAG, WORKSIZE(2097152),
      NOMLOGIC, NUMBER, OBJECT, NORENT, NORLDR, STMT, NOLIBMAC,
      TERMINAL, TEST, NOXREF(SHORT)
    SYSPARM()
    READY

(4) link sample1 test

    READY

```

1. After your data set is created, place yourself at READY mode of TSO/E.

2. The command to assemble a program is ASM:

- ASM requires, as the first operand, the name of the data set that contains the program to be assembled.

In this example, all you specify is SAMPLE1, because TSO/E naming conventions places your prefix (usually your user ID) to the left of the name you enter, and the type ASM to the right, yielding the fully-qualified name '*prefix*.SAMPLE1.ASM'.

- The ASM command assembles your program and produces an output object module. This will be placed in the data set '*prefix*.SAMPLE1.OBJ', which will be created automatically if it does not exist.
- You can specify assembler options after the data set name. The example requests the TEST option, which allows you to access internal symbols in your program. You will see the effect of this under the TEST command.

3. After the assembly is done, you should receive the final diagnostics, NO STATEMENTS FLAGGED.

If you have assembly errors, correct your source code and reassemble until you have no errors.

4. After the program is assembled, use the LINK command to link-edit it.

- As its first operand, the LINK command requires the name of the data set containing the object module to be link-edited.

Again, the name SAMPLE1 suffices because TSO/E naming conventions places your prefix on the left, and the type OBJ on the right, yielding '*prefix*.SAMPLE1.OBJ'.

- Similar to ASM, you can specify link-edit options on the command. TEST is the option specified, and it continues to allow you to access internal symbols.
- The output of the LINK command is a load member of a partitioned data set (PDS). The default data set is '*prefix*.SAMPLE1.LOAD(TEMPNAME)', which is automatically created if it does not exist.

Now that your program is in load module form, you can execute it using the TEST command.

```
(5) test sample1
(6) TEST

(7) go
(8) IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
(9) TEST

(10) help

SUBCOMMANDS -
  ASSIGN, AND, AT, CALL, COPY, DELETE, DROP, END, EQUATE, FREEMAIN, GETMAIN, GO,
  LIST, LISTDCB, LISTDEB, LISTMAP, LISTPSW, LISTTCB, LISTVSR, LOAD, OFF, OR,
  QUALIFY, RUN, WHERE.
IKJ56804I FOR MORE INFORMATION ENTER HELP SUBCOMMANDNAME OR HELP HELP
TEST

(11) end
(12) READY
```

5. The TEST command requires just the name of the program to test.

Again, you need only specify SAMPLE1, because TSO/E supplies the prefix on the left and the TEST command assumes the type LOAD. Also, the default member name is TEMPNAME, yielding the data set '*prefix*.SAMPLE1.LOAD(TEMPNAME)'.

6. TEST displays a TEST mode message, indicating that it is your turn to enter TEST subcommands to control TEST's processing.

Right now, your program has been loaded into storage, but has not yet started execution.

7. Run your program with the GO subcommand.

This subcommand tells TEST to start executing the program wherever it left off (in this case, at the start of the program), and continue until the program stops.

8. The program runs to normal completion, meaning there was noabend.

9. TEST returns control to the terminal with another mode message.

Now that the program has executed, you may wish to use other TEST subcommands to view and alter the program.

10. The HELP subcommand provides a list of the TEST subcommands.

HELP also describes the function, syntax, and operands of the the TEST command (not shown).

11. To terminate TEST processing, use the END subcommand.

12. TEST returns to READY mode.

So far, you have seen how to get a program ready for TEST using foreground assembly and link-edit, how to invoke TEST, run the program, and terminate the TEST session.

## Viewing a Program in Storage

One function you will need when executing under TEST is to view the contents of your data items and registers.

The LIST subcommand (abbreviated "L") provides this facility, and it requires just one operand — the register(s) or address(es) of storage you want to view.

When using TEST, you specify what you want to work with via an *address*. There are several forms of addresses: registers, symbolic, relative, absolute, and indirect, as you will see in the following examples.

This section of the tutorial shows you the LIST subcommand of TEST and uses LIST to demonstrate the various forms of the addresses you can use on the TEST subcommands.

You will need to view the source code for SAMPLE1 while performing the following exercise; a listing of it appears in [“Example programs for the TEST tutorial” on page 125](#).

```

(1) test sample1
    TEST
(2) list 0r
    0R 0001AD0C
    TEST
(3) list 5r:8r
    5R FFFFFFFF 6R FFFFFFFF 7R FFFFFFFF 8R FFFFFFFF
    TEST
(4) list 14r:3r
    14R 0000B82C 15R 0001CF68 0R 0001AD0C 1R 0001BFB0
    2R FFFFFFFF 3R FFFFFFFF
    TEST
(5) list (3r 9r 11r)
    3R FFFFFFFF
    9R FFFFFFFF
    11R FFFFFFFF
    TEST
(6) go
    IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
    TEST
(7) list 0r:15r
    0R 0001AD0C 1R 0001BFB0 2R FFFFFFFF 3R FFFFFFFF
    4R FFFFFFFF 5R FFFFFFFF 6R FFFFFFFF 7R FFFFFFFF
    8R FFFFFFFF 9R FFFFFFFF 10R FFFFFFFF 11R FFFFFFFF
    12R FFFFFFFF 13R 0001BFB8 14R 0000B82C 15R 0001CF68
    TEST

```

1. Test your program again, stopping at the start of your program.
2. To see the contents of a register, use the LIST subcommand, specifying the register number followed by the letter "R", meaning "register".

Hint: Be careful not to get confused with a common programming convention of naming the registers "R0", "R1", and so on. Under TEST, such names would designate a main storage location, as you will see later.

3. At times you may wish to view a consecutive range of registers. The notation for this is a colon separating the two registers of the range.

This subcommand requests registers 5 through 8.

4. Note that registers can wrap around, so you may specify a higher register number first.

5. You may wish to view the contents of a list of registers. In this case, you must enclose the list in parentheses and separate each register in the list with a comma or a blank.

This subcommand requests the contents of registers 3, 9, and 11.

6. Now execute the program.

7. This subcommand displays all of the registers, after the program has terminated.

Note that TEST initializes registers 2 through 12 with X'FFFFFFFF' to allow you to see which registers are changed by the tested program.

The above examples of registers show the three standard forms in which addresses can be specified on the TEST subcommands:

- A single address
- A range of addresses (separated by a colon)
- A list of addresses (enclosed in parentheses and separated by blanks or commas)

This is true whether the addresses are registers or main storage locations.

```
(8) list charcon
    CHARCON  TEST EXAMP
    TEST

(9) list fullcon
    FULLCON  -1
    TEST

    list halfcon
    HALFCON  +32
    TEST

(10) list adcon
    ADCON    118676
    TEST

    list hexcon
    HEXCON    0000001F
    TEST

    list packcon
    PACKCON   +25
    TEST

    list bincon
    BINCON    10101100
    TEST

(11) list charcon:bincon
    CHARCON   TEST EXAMP...*.
    TEST

(12) list (adcon packcon 5r)
    ADCON     118676
    PACKCON   +25
    5R        FFFFFFFF
    TEST
```

Viewing the contents of main storage locations is just as easy as viewing registers. All you need to specify is the address or addresses of the locations you want to view.

Because you assembled and link-edited your program with the TEST option, you will be able to view the contents of your program by using the symbolic names on your data items and instructions.

8. This causes TEST to display the contents of CHARCON in character form. TEST chooses character because you defined the item in your assembler code as CL10.
9. Listing a fullword or halfword item causes TEST to convert the value to a signed decimal number, which is easier to read than binary.
10. Here are the other data items in the program, listed with the default characteristics implied by their definition.
11. Again, you may use the range and list forms of the LIST subcommand. This subcommand displays all of the storage between CHARCON and BINCON. TEST uses the first data type to determine how to display the storage.

**Note:** A dot indicates an unprintable character.

12. Here is a list of addresses, in parentheses. You can mix registers and storage locations in the list.

```

(13) list save
      SAVE
        +0 +0
        +4 +114616
        +8 +0
        +C +0
        +10 +0
        +14 +0
        +18 +0
        +1C +0
        +20 +0
        +24 +0
        +28 +0
        +2C +0
        +30 +0
        +34 +0
        +38 +0
        +3C +0
        +40 +0
        +44 +0
      TEST

(14) list fullcon:bincon
      FULLCON
        +0 -1
        +4 +31
        +8 +2155461
        +C -488423227
        +10 -406727465
        +14 +604
        +18 -1409285540
      TEST

```

13. Notice that displaying an item defined with a duplication factor causes TEST to recognize this in its format.
14. Sometimes LIST's default data type is not very helpful; here all the storage after FULLCON is treated as fullwords.

**Note:** The default is the type specified in the program for the first item in the range.

```
(15) list bitcon
(16) IKJ57280I ADDRESS BITCON NOT FOUND+
      IKJ56703A REENTER THIS OPERAND -
(17) ?
      IKJ57280I BITCON NOT IN INTERNAL SYMBOL TABLE FOR TEMPNAME . SAMP1
(18) |
      TEST
(19) list stop1
      STOP1
          +0    LH    R3,122(,R12)
      TEST
      list stop2
      STOP2
          +0    A     R3,114(,R12)
      TEST
      list stop3
      STOP3
          +0    ST    R3,118(,R12)
      TEST
(20) list stop1:stop3
      STOP1
          +0    LH    R3,122(,R12)
          +4    A     R3,114(,R12)
          +8    ST    R3,118(,R12)
      TEST
(21) list (stop1 stop3)
      STOP1
          +0    LH    R3,122(,R12)
      STOP3
          +0    ST    R3,118(,R12)
      TEST
```

15. This is a sample of an error, because the symbol BITCON does not exist in the program.

16. TEST asks you to reenter the incorrect address.

A "+" sign at the end of a message means that more information is available.

17. You can obtain this extra information by typing "?" with nothing else on the line.

18. To cancel the erroneous subcommand and return to the TEST mode, press the attention key. This produces the "|" symbol on the screen.

19. TEST also allows you to display instructions. You see the explicit assembler form.

20. This subcommand shows a range of instructions.

21. This subcommand shows a list of instructions.



```

(22) list charcon x
      CHARCON
      +0  E3C5E2E3 40C5E7C1 D4D7
      TEST

(23) list fullcon x
      FULLCON  FFFFFFFF
      TEST

(24) list fullcon:bincon x
      FULLCON
      +0  FFFFFFFF 0000001F 0020E3C5 E2E340C5
          E7C1D4D7 0000025C AC
      TEST

(25) list charcon x length(5)
      CHARCON  E3C5E2E3 40
      TEST

(26) list save x multiple(5)
      SAVE
      +0  00000000
      +4  0001BFB8
      +8  00000000
      +C  00000000
      +10 00000000
      TEST

      list charcon length(2) multiple(5)
      CHARCON
      +0  TE
      +2  ST
      +4  E
      +6  XA
      +8  MP
      TEST

(27) list save:bincon print(sample1)
      TEST

```

Now, for some other operands of LIST. You may wish to read the syntax of the LIST subcommand of TEST in *z/OS TSO/E Command Reference* at this time.

22. After the address on LIST, you can specify a data type that TEST should use to display storage. This overrides the defined data type of the symbol.

This requests TEST to display CHARCON in hexadecimal.

23. Here is FULLCON displayed in hexadecimal.

24. Here is a range of storage, also in hexadecimal.

25. The *length* operand specifies the number of bytes you want to have displayed. This overrides the defined length of the symbol.

26. The *multiple* operand allows you to specify a multiplicity factor for the item. You can use this to display a table, or to format a long area for readability.

27. The *print* operand allows you to specify a data set, rather than the terminal, to which the list should be directed. You may later print the data set to read the information easily.

The name of the data set that will contain the list consists of the name you specify, preceded by your prefix and followed by TESTLIST as the descriptive qualifier. Therefore, in this example, the information will be placed in '*prefix*.SAMPLE1.TESTLIST'.

```

(28) where charcon
(29) 1CFEA. LOCATED AT +82 IN TEMPNAME.SAMP1 UNDER TCB LOCATED AT 7C2560.
TEST
(30) list 1cfea.
      0001CFEA. E3C5E2E3
TEST
(31) list 1cfea. c length(5)
      0001CFEA. TEST
TEST
(32) list +82 length(8)
      +82 E3C5E2E3 40C5E7C1
TEST
(33) list save+20
      0001CFB4. 00000000
TEST
(34) list save+32n
      0001CFB4. 00000000
TEST
(35) list save-10
      0001CF84. 5030C076
TEST
(36) where save-10
      1CF84. LOCATED AT +1C IN TEMPNAME.SAMP1 UNDER TCB LOCATED AT 7C2560.
TEST
(37) list +1c
      +1C 5030C076
TEST

```

So far, you have seen the various operands of the LIST subcommand of TEST. All addresses were specified as *symbolic* addresses. Normally, your symbolic names cannot be referenced at execution time, but using the TEST operand on the ASM and LINK commands caused your symbols to be available at execution time.

Other forms of addresses besides symbolic are absolute, relative, indirect, and address expressions, as shown below.

28. To obtain the absolute address of data or an instruction, use the WHERE subcommand.

This example is requesting the location of CHARCON.

29. TEST gives the absolute address and the address relative to the CSECT.
30. To use an absolute address in a LIST command, follow the address with a period. The period is a signal that you have entered an absolute address and not a register number or a symbolic address.

Because TEST does not know the data type of this address, it displays the data in hexadecimal, for the default length of four.

31. Using the data type and length operands lets you control how much storage is displayed, and in what format.
32. A *relative* address is indicated by a plus sign followed by a hexadecimal number. It represents the displacement of something from the beginning of the CSECT. (Later you will be able to change this "base" address.)
33. This is an *address expression*, meaning a symbolic, absolute, or relative address followed by a plus or a minus sign, followed by a hexadecimal number (modifying value).

34. If you prefer to express the modifying value in decimal, you must follow the number with the letter "n".
- "+32n" is the same as "+20".
35. Here is a negative modifying value.
36. Just to check the address involved, WHERE tells you the absolute and relative addresses of SAVE-10.
37. This displays the same storage location as SAVE-10.

```
(38) list 1r
      1R 0001BFB0
      TEST

(39) list 1bfb0.
      0001BFB0. 8001BFB4
      TEST

(40) list 1r%
      0001BFB0. 8001BFB4
      TEST

(41) list 1r%%
      8001BFB4. 00000000
      TEST

      end

      READY

(42) listcat
      IN CATALOG:USERCAT
      USER01.SAMPLE1.ASM
      USER01.SAMPLE1.LOAD
      USER01.SAMPLE1.OBJ
      USER01.SAMPLE1.TESTLIST
      READY
```

Now to look at *indirect* addresses.

38. Viewing the contents of a register, as you have already seen.
39. Here is the data at the address specified in register 1.
40. Specifying a "%" or a "?" after a register says you want to view, not the register, but the data to which the register points.

This subcommand produces the same result as the previous two subcommands.

When you use "%", the effective address is treated as a 24-bit address. When you use "?", the effective address is treated as a 31-bit address.

41. You can stack "%" and "?" signs to indicate multiple levels of indirect addressing.

This means go to the address to which register 1 points, and then use that as an address, and view the data there.

42. After ending TEST, a LISTCAT command displays the data sets involved so far. Notice that the SAMPLE1.TESTLIST data set was created from your LIST subcommand with the PRINT operand.

In this section of the tutorial, you have seen several examples of the LIST subcommand to view registers and storage. You have also seen the three general forms of address operands on TEST subcommands:

- Single address
- Range of addresses
- List of addresses.

Finally, you have seen the various types of addresses:

- Symbolic
- Absolute
- Relative
- Indirect
- Expressions
- Registers

## Monitoring and Controlling Program Execution

---

So far, you have simply executed your program from start to finish, viewing storage before execution began and after the program terminated. TEST also allows you to interrupt execution of your program at selected points so that you can use the TEST subcommands to view storage and perform other functions. The points at which execution is interrupted are known as *breakpoints*.

You establish breakpoints with the AT subcommand of TEST. Whenever TEST encounters a breakpoint, it returns control to you at the terminal. You can inspect and modify storage and registers, and then resume execution at the breakpoint or elsewhere. This facility allows you to monitor your program execution.

You can remove breakpoints with the OFF subcommand.

```
(1) test sample1
    TEST
(2) at stop1
    TEST
(3) at stop3
    TEST
(4) go
(5) IKJ57024I AT STOP1
    TEST
(6) go
(7) IKJ57024I AT STOP3
    TEST
(8) go
    IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
    TEST
(9) off
    TEST
(10) go +0
    IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
    TEST
```

1. You are testing program SAMPLE1 again.
2. The AT subcommand establishes breakpoints at one or more instructions in your program.  
This is setting a breakpoint at the label STOP1.
3. This sets another breakpoint at the label STOP3.
4. Start execution of the program.
5. When TEST encounters a breakpoint, it returns control to the terminal.  
You receive control *before* execution of the instruction where the breakpoint was placed.
6. The GO subcommand resumes execution at the point it was interrupted.

7. The program stops at the second breakpoint and returns control to the terminal.
8. The last GO causes the program to run to completion.
9. The OFF subcommand with no operands removes all breakpoints from the program.
10. The GO subcommand with an address causes TEST to restart execution from that address. "+0" is the relative address of the start the program, so this subcommand causes TEST to re-execute the program from the beginning.

**Note:** Register contents are *not* reset to the original entry values when you execute this command.

Because there are no breakpoints, the program runs to completion.

```
(11) at stop1:stop3
    TEST

(12) go +0
    IKJ57024I AT STOP1
    TEST

(13) list 3r
    3R FFFFFFFF
    TEST

(14) go
    IKJ57024I AT +4 FROM STOP1
    TEST

(15) list 3r
    3R 00000020
    TEST

(16) at stop1:stop3 (list 3r)
    TEST

(17) go +0
(18) IKJ57024I AT STOP1
    3R 00000020
    TEST

(19) go
    IKJ57024I AT +4 FROM STOP1
    3R 00000020
    TEST

    go
    IKJ57024I AT +8 FROM STOP1
    3R 0000001F
    TEST

    go
    IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
    TEST
```

11. By specifying a range of addresses on the AT subcommand, you can cause TEST to stop at every instruction in the range. This allows you to "instruction step" through your program.
12. Start from the beginning of the program again.
13. View the contents of register 3 at the STOP1 breakpoint.
14. Continue execution.
15. View register 3 again.

If you want to perform some standard action, such as listing registers or storage, every time TEST hits a breakpoint, you may include a list of TEST subcommands on the AT subcommand.

The list of subcommands, even if it is only one subcommand, must be enclosed in parentheses after the address(es) of the breakpoint(s).

16. This is requesting TEST to list the contents of register 3 before it returns control to you at a breakpoint.

This action overrides the previous breakpoints established at STOP1 through STOP3. (You don't have to issue an intervening OFF.)

17. Run the program from the beginning once more.
18. TEST displays register 3 before giving control to the terminal.
19. You must still enter GO to continue execution.

```
(20) at stop1:stop3 (list 3r;go)
      TEST
(21) go +0
      IKJ57024I AT STOP1
      3R 00000020
      IKJ57024I AT +4 FROM STOP1
      3R 00000020
      IKJ57024I AT +8 FROM STOP1
      3R 0000001F
      IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
      TEST
(22) off (stop1 stop2)
      TEST
(23) go +0
      IKJ57024I AT +8 FROM STOP1
      3R 0000001F
      IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
      TEST
end
READY
```

20. If you do not want to type GO after every breakpoint, include GO in the list of subcommands.

The individual subcommands must be delimited by semicolons within the parentheses.

21. Start from the beginning again. TEST displays register 3 at every breakpoint, but does not give control to the terminal because of the GO subcommand.

The program runs to completion.

22. You can selectively remove breakpoints by specifying the address(es), either single, list, or range, on the OFF subcommand.

This is removing a list of breakpoints (at addresses STOP1 and STOP2). The breakpoint at STOP3 remains.

23. Running from the beginning, TEST shows the breakpoint at STOP3 only, with no stops made.

In this section of the tutorial, you have seen how to interrupt the execution of your program by establishing breakpoints at instructions of your choice. You can do this when you first enter TEST, before your program starts executing. Of course, you can add additional breakpoints at any time during TEST processing.

To remove breakpoints, use the OFF subcommand of TEST.

You can start execution at any point in your program by specifying an address on the GO subcommand of TEST.

## Altering Storage and Registers

TEST provides subcommands with which you can alter the contents of main storage and registers. Two subcommands used in this tutorial are the assignment function and the COPY subcommand. Assignment allows you to alter storage or registers by entering a new value from the terminal. COPY allows you to move data from one storage location or register to another.

You can use these functions in preparing test cases:

- To "set up" various combinations of data items, causing different sections of your program to be executed.
- To make temporary "fixes" while your program is running.

```
(1) test sample1
    TEST
(2) charcon=c'abcde'
    TEST
(3) list charcon
    CHARCON  abcdeEXAMP
    TEST
(4) charcon=c'ABCDE      '
    TEST
    list charcon
    CHARCON  ABCDE
    TEST
(5) 5r=f'100'
    TEST
    list 5r
    5R  00000064
    TEST
```

1. Execute TEST for your program again.
2. This is an example of the assignment function. CHARCON is given the character ("c") value 'abcde'.  
There is no subcommand name for assignment. Just type the receiving field followed by an equal sign, followed by the data type (same as for LIST), and the value in quotes.
3. Notice that the assignment works somewhat differently than an assembler language "DC" in that it does not pad character strings with blanks.  
Also, if you enter your characters in lower case, they are not translated to upper case.
4. To get upper case and padding with blanks, explicitly request it in the value you are assigning.
5. Here is an assignment to a register. (Note the padding to the left with zeros.)

```
(6) list (hexcon fullcon) x
    HEXCON 0000FD38
    FULLCON FFFFFFFF
    TEST

(7) copy hexcon fullcon
    TEST

(8) list (hexcon fullcon) x
    HEXCON 0000FD38
    FULLCON 0000FD38
    TEST

(9) charcon=c'ABCDEFGHJIJ'
    TEST

    list charcon
    CHARCON ABCDEFGHIJ
    TEST

(10) copy charcon charcon+3
    TEST

    list charcon
    CHARCON ABCABCDHIJ
    TEST

(11) CHARCON ABCABCDHIJ
    TEST

(12) charcon=c'ABCDEFGHJIJ'
    TEST

(13) copy charcon charcon+1 L(6)
    TEST

(14) list charcon
    CHARCON AAAAAAAHIJ
    TEST
```

6. View the contents of HEXCON and FULLCON.

7. The COPY subcommand requires two operands: the "from" address and the "to" address. It always moves four bytes by default.

Here, COPY moves the contents of HEXCON to FULLCON.

8. Because both of the items are four bytes long, their contents are the same now.

9. Assign a new value to CHARCON.

10. Issue the COPY subcommand for the area where the fields overlap.

11. TEST picks up the first four bytes of CHARCON and moves it to CHARCON+3.

12. Set up CHARCON again.

13. Now the "to" field address is just one byte greater than the "from" field address. Also, a length of six bytes is specified with the LENGTH operand, "L(6)".

14. In this situation, the first byte of the "from" location is propagated for the specified length.



```

(15) list 14r:1r
      14R 0000B82C 15R 0001CF68 0R 0001AD0C 1R 0001BFB0
TEST

(16) copy 14r save+12n L(16)
      TEST

(17) list save+12n L(16) x
      0001CFA0. 0000B82C 0001CF68 0001AD0C 0001BFB0
TEST

(18) list stop1 x L(4)
      STOP1 4830C07A
TEST

(19) where stop1
      1CF7C. LOCATED AT +14 IN TEMPNAME.SAMP1 UNDER TCB LOCATED AT 7C2850.
TEST

(20) 6r=f'0'
      TEST

(21) copy stop1 6r
      TEST
      list 6r
      6R 4830C07A
TEST

(22) copy stop1 6r pointer
      TEST
      list 6r
      6R 0001CF7C
TEST

end

READY

```

15. View registers 14, 15, 0, and 1.
16. You can use COPY to restore registers. In this case, the registers are considered contiguous storage, so the LENGTH operand picks up 16 bytes of registers starting from register 14 (registers 14, 15, 0, and 1), and moves the information to SAVE+12n (remember, the "n" means decimal).
17. View the saved registers.
18. View the instruction STOP1.
19. Obtain the address of the instruction STOP1.
20. Clear register 6 (all zeros).
21. Copying storage to a register "loads" that storage into the register.
22. Issuing the same command, but with the POINTER operand, causes TEST to move, not the data at STOP1, but rather the address of STOP1, to the register, (in effect, performing a Load Address).

In this section of the tutorial, you have seen several examples of the assignment function and the COPY subcommand of TEST.

Assignment allows you to alter the contents of storage or registers by supplying a new value from the terminal. You must also specify the data type of the value you are assigning.

COPY allows you to move data from registers or storage to other registers or storage. It is roughly equivalent to the various Move, Load, and Store instructions available in System/370 Assembler Language.

## Using Additional Features of TEST

---

You have been introduced to the basic features of TEST, so that you are now able to view your program in storage, modify your program in storage, monitor your program's execution using breakpoints, and restart execution at any point in your program. You have also seen the various forms of addresses used on TEST subcommands.

This section of the tutorial shows you some of the additional features of TEST, including the specialized LIST subcommands and some further addressing possibilities.

The exercise in this section uses the IKJSAMP2 member of SYS1.SAMPLIB. To perform this exercise at your terminal, create a data set called '*prefix*.SAMPLE2.ASM' and copy the source code from 'SYS1.SAMPLIB(IKJSAMP2)' into your data set. A copy of the source code and assembler listing for the sample program used in this exercise are also included in ["Example programs for the TEST tutorial"](#) on [page 125](#).

The source program in SAMPLE2.ASM will assemble and link-edit correctly, but it will not run to normal completion. There is an error in the program that you will locate and fix during the following TEST session.

**Note:** The program in SAMPLE2.ASM was assembled for this exercise on an MVS/370 system. The assembler output will not match what is shown here. Therefore, you should skip the assemble step in the tutorial (step 1) and copy 'SYS1.SAMPLIB(IKJOB2)' into your own data set called '*prefix*.SAMPLE2.OBJ'.

```

READY
(1) asm sample2 test
    ASSEMBLER (XF) DONE
    NO STATEMENTS FLAGGED IN THIS ASSEMBLY
    HIGHEST SEVERITY WAS      0
    OPTIONS FOR THIS ASSEMBLY
        ALIGN, ALOGIC, BUFSIZE(STD), NODECK, NOESD, FLAG(0),
        LINECOUNT(55), NOLIST, NOMCALL, YFLAG, WORKSIZE(2097152),
        NOMLOGIC, NUMBER, OBJECT, NORENT, NORLD, STMT, NOLIBMAC,
        TERMINAL, TEST, NOXREF(SHORT), SYSPARM()
    READY
(2) link sample2 test
    READY
(3) alloc dd(outdd) da(*)
    READY
(4) test sample2
    TEST
(5) at addit
    TEST
(6) go
(7) IKJ57024I AT ADDIT
    TEST
(8) listmap
    REGION SIZE 007FB000 AT ADDRESS 00005000
    REGION SIZE 7D800000 AT ADDRESS 02800000
    UNDER TCB AT 007C2AA8
        PROGRAM NAME  LENGTH  LOCATION
        TEMPNAME      000000B0 0001CF50
    ACTIVE RBS:  TYPE  PROGRAM-ID
                PRB   TEMPNAME
    SUBPOOL INFORMATION:
    NUMBER  LOCATION  LENGTH
    0       0001B000  00001000
    78      0000B000  00001000
    IKJ57395I MAP COMPLETE
    TEST

```

1. Assemble your SAMPLE2.ASM data set with the TEST operand.
2. Link-edit the data set with the TEST operand.
3. This program requires an output data set with a ddname of OUTDD. The ALLOC command of TSO/E is the equivalent of a JCL DD statement. This command allocates the ddname OUTDD to the terminal by specifying "DA(\*)".
4. Test the load module.
5. Set a breakpoint at the label ADDIT.
6. Start execution.
7. The program stops at the breakpoint.
8. The LISTMAP subcommand of TEST provides a map of the storage in your region.

LISTMAP is one of the specialized LIST subcommands. Like LIST, it has an optional PRINT operand that allows you to specify the name of a data set to which you would like the output of the subcommand directed.

```
(9) listpsw
IKJ57652I PSW LOCATED AT 7B8208
  XRXXXTIE  KEY  XMWP  AS  CC  PROGMASK  EA  BA  INSTR ADDR
  01000111  8   1101  00  01   0000     0  1   0001DEBE
TEST

(10) listpsw addr(20.)
IKJ57652I PSW LOCATED AT 20
  XRXXXTIE  KEY  XMWP  AS  CC  PROGMASK  EA  BA  INSTR ADDR
  01000111  8   1101  00  10   0000     0  1   00CB9D60
TEST

(11) listdcb outdcb
IKJ57652I DCB LOCATED AT 01DF9C
DEVICE INTERFACE SEGMENT
  RELAD  KEYCN  FDAD  DVTBL  KEYLE  DEVT  TRBAL
  00000000  00   0000000000000000  000000  00   4F  0000

COMMON INTERFACE
  BUFNO  BUFCB  BUFL  DSORG  IOBAD
  01     01EFC0 0000  4000  00000001

FOUNDATION EXTENSION
  HIARC-BFTEK-BFALN  EODAD  RECFM  EXLST
  06                 000001  80    000000

FOUNDATION
  TIOT  MACRF  IFLGS  DEBAD  OFLGS
  0504 0050   00    7B7A24  92
TEST

(12) listdcb outdcb field(dcbdebad)
IKJ57652I DCB LOCATED AT 01DF9C
DEBAD
7B7A24
TEST
```

9. The LISTPSW subcommand displays the contents of the PSW, the current PSW by default.

10. With the ADDR operand, you can specify the address of the PSW you wish to see.

LISTPSW also has the PRINT operand.

11. The LISTDCB subcommand lists the contents of the DCB, with fields labelled. You must specify the address of the DCB you wish to view, because TEST cannot choose a suitable default.

This subcommand is displaying the DCB in your program.

12. If you wish to see only selected fields of the DCB, use the FIELD operand. In parentheses, you can specify one or more field names (standard DSECT names) that you wish to have displayed.

LISTDCB also has the PRINT operand.

```

(13) listdeb 7b7a24.

IKJ57652I DEB LOCATED AT 7B7A24
BASIC SECTION
NMSUB  TCBAD  AMLNG  DEBAD  OFLGS  IRBAD  OPATB  QSCNT  FLGS1  RESERVED
01      7B2588  10      000000  C8      000000  0F      00      11      00
NMEXT  USRPG  PRIOR  ECBAD  PROTG/DEBID  DCBAD  EXSCL  APPAD
01      000000  FF      000000  8F      01DF9C  02      7B7A00
IKJ57334I DEB DOES NOT HAVE A DIRECT ACCESS SECTION+
TEST

(14) equate outdeb 7b7a24.

TEST

(15) listdeb outdeb

IKJ57652I DEB LOCATED AT 7B7A24
BASIC SECTION
NMSUB  TCBAD  AMLNG  DEBAD  OFLGS  IRBAD  OPATB  QSCNT  FLGS1  RESERVED
01      7B2588  10      000000  C8      000000  0F      00      11      00
NMEXT  USRPG  PRIOR  ECBAD  PROTG/DEBID  DCBAD  EXSCL  APPAD
01      000000  FF      000000  8F      01DF9C  02      7B7A00
IKJ57334I DEB DOES NOT HAVE A DIRECT ACCESS SECTION+
TEST

(16) drop outdeb

TEST

```

13. The LISTDEB subcommand is similar to the LISTDCB command, in that you must specify the address of the DEB that you wish to view.

It also has the optional FIELD and PRINT operands.

14. With the EQUATE subcommand, you can add additional symbols to your TEST session, or you can override the address or attributes of existing symbols.

The example is equating the symbol OUTDEB to the absolute address of the DEB. Additional operands on EQUATE would allow you to specify the data type, length, and multiplicity of the symbol.

EQUATE is useful for providing symbolic names to storage locations that are otherwise addressable only via absolute or relative addresses.

15. List the DEB now using the symbolic name from the EQUATE.
16. The DROP subcommand removes symbols added with the EQUATE subcommand. It can remove all symbols, by specifying no operands, or it can remove selective symbols, as in this example.

(17) listtcB

IKJ57652I TCB LOCATED AT 7B2588  
RBP PIE DEB TIO CMP TRN MSS PKF  
007FE8F0 00000000 007B7A24 007CA000 00000000 4401B798 7FFFDAA8 80

FLGS LMP DSP LLS JLB JPQ  
0000000001 FF FF 007C2818 0001AD0C 00000000

GRS  
R0 R1 R2 R3  
000000001 0001B798 007FE028 7FFFE070  
R4 R5 R6 R7  
007B2588 00FDD630 007FE8F0 007FE8F0  
R8 R9 R10 R11  
01DE619E 0001B798 01DE519F 02902108  
R12 R13 R14 R15  
81DE41A0 02902108 02902270 80FF30BA

FSAB TCB TME JSTCB NTC OTC LTC IQE  
01CFB8 00000000 00000000 007C2E88 00000000 007B2290 00000000 00000000

ECB TSFLG STPCT TSLP TSDP PQE/RD AQE/AE NSTAE STABB TCT  
000097E0 00 01 00 00 7FF1451C 00000000 00 7EAFB0 807F9200

USER NDSP0 NDSP1 NDSP2 NDSP3 RESERVED JSCB SSAT IOBRCL  
00000000 00 00 40 00 00000000 007B81C4 00FDB938 00000000

RESERVED EXT1 NDSP4 NDSP5 FLGS6 FLGS7 DAR RESERVED SYSCTL STMCT  
00000000 00000000 00 00 00 00 00 00 00 00

EXT2 AECB XSB BACK RTWA NSSP XLAS ABCURL  
007B26E0 00000000 007FE9C0 007B2290 00000000 00000000 00000000 00

RESERVED TID RESERVED XSCT1 CCPVI FOE SWA STAWA TCBIIDL  
00 00 00 0000 0041 00000000 7F71F238 00000000 E3C3C240

RMT12 ESTAE RESERVED SEQNO AFFN FBYT1-2  
00000000 00000000 7F71E388 0009 FFFF 0000

RESERVED ERD EAE  
C0000000000000000000007C1DD800000000 7FF1452C 00000000

TCB EXTENT  
TFLG GTFA RESERVED RCMP EVENT TQE CAUF PERCP PERCT  
00 000000 00 000000 00000000 00000000 00000000 00000000 00000000

17. The LISTTCB subcommand is the last of the specialized LIST subcommands. By default, it displays the current TCB, but by using the ADDR operand (like LISTPSW) you can display any TCB.

It also has the optional PRINT operand.

```

(18) off
      TEST

(19) go
      IKJ56641I TEMPNAME ENDED DUE TO ERROR
      IKJ56640I SYSTEM ABEND CODE 0C9   REASON CODE 0009
      TEST

(20) where
      1DED2.  LOCATED AT +3A  IN TEMPNAME.TABAVG  UNDER TCB LOCATED AT 7B2588.
      TEST

(21) list 4r:7r
      4R 00000000  5R 0000016E  6R 00000018  7R 00000000
      TEST

(22) 7r=f'12'
      TEST

      list 7r
      7R 0000000C
      TEST

(23) go 1ded0.
      TABLE AVERAGE PROGRAM
      IKJ57023I PROGRAM UNDER TEST HAS TERMINATED NORMALLY+
      TEST

(24) list (sum avg)
      SUM  +366
      AVG
          +0  +6
          +4  +30
      TEST

```

Execute the program again. It had stopped at the breakpoint at ADDIT.

18. Remove the breakpoint so that the program will run to completion.
19. GO continues execution. The program does not complete normally. The abend code for the program is 0C9, which indicates that a fixed-point-divide exception occurred (division by zero).

If the abend information does not appear on your screen as shown, enter a question mark.

20. The WHERE subcommand returns the failing location and the displacement within the CSECT.

Looking at the source for SAMPLE2, you can see that the failing instruction is really the one prior, the DR. This instruction is two bytes before the "failing location" shown by the WHERE subcommand.

21. Viewing the registers, register 7 contains zero, and the program is dividing by register 7.
22. Put the correct value in register 7 for the divide (the number of elements in the table is 12).

This provides a temporary "fix" for the problem.

23. Restart the program from the DR instruction.

The program now runs to normal completion.

24. View the program's result fields.

The example on this page shows how to determine the abend code and the failing instruction if your program under TEST should not complete normally.

## More TEST subcommands

```
(25) where +10
      1DEA8.  LOCATED AT +10 IN TEMPNAME.TABAVG UNDER TCB LOCATED AT 7B2588.
TEST

(26) qualify outdcb
      TEST

(27) where +10
      1DFAC.  LOCATED AT +114 IN TEMPNAME.TABAVG UNDER TCB LOCATED AT 7B2588.
TEST

(28) list +10
      +10  004F0000
      TEST

(29) list outdcb+10
      0001DFAC.  004F0000
      TEST

(30) qualify tempname.tabavg
      IKJ57277I QUALIFICATION IS UNDER TCB AT 7B2588
      TEST

(31) where +10
      1DEA8.  LOCATED AT +10 IN TEMPNAME.TABAVG UNDER TCB LOCATED AT 7B2588.
TEST

      end

      READY
```

Earlier in the topic on addressing, it was stated that relative addresses are calculated in relationship to the start of the CSECT currently active. The following examples show you how to alter this "base" address for relative addresses.

25. Find out where +10 is currently located.
26. The QUALIFY subcommand changes the base address for relative addresses. Now any relative addresses will be calculated from the address of OUTDCB, rather than from the start of the CSECT.
27. The address +10 is now at a different absolute location (+114 from the start of the CSECT).
28. View the contents of +10.
29. View the OUTDCB+10; these are now the same location.
30. To return to a base of the CSECT, use QUALIFY again with the qualified address of the CSECT (the load module name, TEMPNAME), followed by a period, then the CSECT name (in this case, TABAVG).
31. Now the relative address +10 is calculated from the CSECT.

Qualified address are useful when you are working with more than one CSECT, or more than one load module in storage. By qualifying a symbolic or relative address with the load module name and the CSECT name, you can alternate between programs, viewing and altering storage.

## More TEST Subcommands

---

So far, this tutorial has shown you some of the subcommands of TEST, what they can do for you, and some of the variations you can use. There are still more versions of these subcommands.

### GETMAIN and FREEMAIN

The GETMAIN and FREEMAIN functions of TEST are essentially the same as the system macros. That is, they enable you to acquire additional storage dynamically, and to free it. You must specify the amount of storage and the subpool (default is 0) from which you wish to acquire the storage. On GETMAIN, you can



optionally EQUATE the new storage to a symbol so you do not have to remember the absolute address of it.

GETMAIN and FREEMAIN are useful for maintaining a "scratch pad" with copies of data areas that you need while testing, and especially for "scaffolding" when setting up test cases. You can build your own parameters in the acquired area to send to a routine, and see how the program alters these parameters.

## LOAD and DELETE

At times, you may wish to bring additional programs into storage, or obtain your own copy of a module that normally resides in the link pack area. If your program attempts to LOAD, LINK, XCTL, or ATTACH another module, the system looks for the module in the following search order sequence:

1. TASKLIB
2. STEPLIB
3. JOBLIB
4. LPA
5. LNKLIST

If the module is not in any of these areas, it will not be found. To avoid this, bring the module into virtual storage by using the LOAD subcommand of TEST.

The LOAD command allows you to load a program from a data set. This program will be a fresh copy, placed in your own region, to which you can add breakpoints. (You cannot put breakpoints in LPA-resident modules because they are write-protected.)

DELETE allows you to remove the module from your region.

## CALL

If you wish to invoke a program and pass it parameters, without setting up the parameter list yourself, you can use the CALL subcommand of TEST. You can also specify where CALL should return control. TEST will build a parameter list and set register 1 to its address, and it will set register 15 to the calling address, and register 14 to the return address (if you request). When using CALL, you may want to save registers 1, 14, and 15 prior to the CALL, to protect this information.

An alternative to CALL is to obtain storage with GETMAIN, use assignment and COPY to build the parameter list and set the registers, and use GO to branch to the routine.

## Testing Programs That Use the Vector Facility

---

You can display and alter vector registers by using the LIST, LISTVSR, and SETVSR subcommands of TEST and the TEST assignment function.

You can list vector system parameters by using the LISTVP subcommand of TEST.

Use the AT subcommand of TEST to set breakpoints at the vector opcodes in the same way you use it to set breakpoints in other programs.

Examples showing the use of the LIST subcommand to display the contents of vector registers follow:

### Subcommand Function

#### **LIST 1V(\*) X**

Displays the entire contents of vector register 1 in hexadecimal.

#### **LIST 1V(4) F**

Displays the fourth element in vector register 1 in fullword fixed point binary.

#### **LIST 3V(3):3V(20)**

Displays elements 3 through 20 in vector register 3 in single precision floating point.

### **LIST OV(\*):15V(\*)**

Displays the entire contents of all 16 vector registers in single precision floating point.

### **LIST OW(\*)**

Displays the entire contents of vector register 0 in double precision floating point.

Use the assignment function to modify the contents of the 16 vector registers. Some examples illustrating the use of the assignment function follow:

#### **Subcommand Function**

#### **1V(\*)=X'00000000'**

Sets the entire contents of vector register 1 to hexadecimal zeros.

#### **1V(10)=F'33'**

Sets the tenth element in vector register 1 to decimal 33.

#### **3V(3)=(X'00',X'02')**

Sets elements 3 and 4 of vector register 3 to X'00' and X'02', respectively.

#### **OW(1)=D'+33E+2'**

Sets the first element of vector registers 0 and 1 to the double precision floating point value of +33E+2.

To display the contents of the vector status register, use the LISTVSR subcommand of TEST. LISTVSR works the same as the LISTPSW subcommand. The following example shows the syntax and output of the LISTVSR subcommand after issuing a RESTORE VSR instruction (VSRRS):

```
listvsr
VSR LOCATED AT 7FFF9EF8
RESERVED      VMM      VCT      VIX      VIU      VCH
00000000 00000000  0      00127  00127  00000000  00000000
TEST
```

You can use the LIST subcommand and the TEST assignment function to display and modify the vector mask register. Some examples follow:

#### **Subcommand Function**

#### **OM=X'046C471F'**

Sets the contents of the vector mask register to X'046C471F'

There is one bit in the vector mask register for each vector element. In this example, the number of vector elements, which is also referred to as the section size, is 32 decimal.

### **LIST OM**

Displays the contents of the vector mask register in hexadecimal.

You can use the LISTVP subcommand of TEST to display the number of vector elements (vector section size) and the partial sum number. For example:

```
listvp
IKJ57026I VECTOR SYSTEM PARAMETER
SECTION SIZE: 00256
PARTIAL SUM:  00004
TEST
```

You can use the SETVSR subcommand of TEST to change the vector mask register control mode, update vector count (VCT), update vector interruption index (VIX), and update vector in-use bits (VIU).

The following examples show the use of the SETVSR subcommand.

#### **Subcommand Function**

#### **SETVSR MASK**

Changes the vector mask register control mode.

**SETVSR NOMASK**

Changes the vector mask register control mode.

**SETVSR VCT(X'nnnn')**

Updates the vector count (VCT), where X'nnnn' is the number of vector elements to process.

**SETVSR VIX(X'nnnn')**

Updates the vector interruption index (VIX), where X'nnnn' is the vector element to start processing with.

**SETVSR VIU(X'nn')**

Updates the vector in-use bits (VIU), where X'nn' indicates the active register pairs.

## Testing Programs That Use Extended Addressing

---

You can use the subcommands of TEST to display and modify access registers, and display and modify data in alternate address/data spaces. For information about writing programs that use extended addressing, see *z/OS MVS Programming: Assembler Services Reference ABE-HSP*.

### Displaying and modifying access registers

You can display and modify access registers by using the LIST subcommand and the TEST assignment function.

The following examples show the use of the LIST subcommand to display the contents of access registers:

<b>Subcommand</b>
<b>Function</b>

**LIST 1A**

Displays the contents of access register 1 in hexadecimal.

**LIST 4A F**

Displays the contents of access register 4 in decimal.

**LIST 0A:15A**

Displays the contents of access registers 0 through 15 in hexadecimal.

The following examples show the use of the assignment function to modify the contents of the 16 access registers:

<b>Subcommand</b>
<b>Function</b>

**7A=X'00000000'**

Sets the contents of access register 7 to zeros.

**2A=F'234'**

Sets the contents of access register 2 to decimal 234.

**5A=(X'00',X'11')**

Sets the contents of access registers 5 and 6 to zero and X'11', respectively.

### Displaying and modifying data in alternate address spaces

You can display and modify the contents of storage in alternate address/data spaces by using the AR and ALET keywords on the LIST subcommand and the TEST assignment function. Use the AR keyword to specify the number of the access register to be used to reference data in an alternate address/data space. Use the ALET keyword to specify from one to eight hexadecimal characters that indicate which address/data space is to be referenced.

The following examples show the use of the LIST subcommand to display data in an alternate address/data space.

### **Subcommand Function**

#### **LIST 4AD8. AR(4)**

Displays the contents of the storage at address 4AD8 in the address/data space indicated by access register 4.

#### **LIST 2R? AR(8)**

Displays the contents of the storage at the location pointed to by general register 2 in the address/data space indicated by access register 8.

#### **LIST 1000. ALET(A624)**

Displays the contents of the storage at location 1000 in the address/data space indicated by the ALET value A624.

The following examples show how to modify the contents of storage in alternate address/data spaces:

### **Subcommand Function**

#### **5558.=X'0002' AR(4)**

Sets two bytes of storage at address 5558 in the address/data space indicated by access register 4, to the value X'0002'.

#### **9R?=F'100' ALET(9E00)**

Sets four bytes of storage, located at the address pointed to by general register 9 in the address/data space indicated by the ALET value 9E00, to a value of decimal 100.

## **Copying Data to and from Alternate Address Spaces**

You can use the ARFROM and ALETFROM keywords on the COPY subcommand to copy data from alternate address/data spaces to other locations. Similarly, you can use the ARTO and ALETTO keywords to copy data to storage in alternate address/data spaces. The ARTO and ARFROM keywords allow you to specify the number of the access register to be used to reference data in an alternate address/data space. Use the ALETTO and ALETFROM keywords to specify from one to eight hexadecimal characters that indicate which address/data space is to be referenced.

The following examples show the use of the COPY subcommand to copy data to and from alternate address/data spaces.

### **Subcommand Function**

#### **COPY 13R? 1000. ARTO(5) LENGTH(72)**

Copies 72 bytes starting at the location pointed to by register 13 to location 1000 in the address/data space indicated by access register 5.

#### **COPY 1R? A080. ARFROM(1) ALETTO(40C3A)**

Copies 4 bytes of storage at the location pointed to by register 1 in the address/data space indicated by access register 1 to location A080 in the address/data space indicated by the ALET value 40C3A.

## **Providing Symbolic Names for Locations in Alternate Address Spaces**

You can use the AR and ALET keywords on the EQUATE subcommand to establish symbols to refer to storage locations in alternate address/data spaces. The AR keyword allows you to specify the number of the access register to be used to reference data in an alternate address/data space. Use the ALET keyword to specify from one to eight hexadecimal characters that indicate which address/data space is to be referenced.

The following examples show the use of the EQUATE subcommand to associate a symbolic name with a location in an alternate address/data space.

### **Subcommand Function**

**EQUATE X 2290. AR(5)**

Symbol X refers to the address of location 2290 in the address/data space indicated by access register 5.

**EQUATE Y 1R? ALET(4AC2)**

Symbol Y refers to the address pointed to by general register 1 in the address/data space indicated by the ALET value 4AC2.

## Example programs for the TEST tutorial

---

The following two programs are used in the TEST tutorial. The first program is used early in the tutorial and must be placed in a sequential data set named '*prefix*.SAMPLE1.ASM'. The second program is used later in the tutorial and must be placed in a sequential data set named '*prefix*.SAMPLE2.ASM'.

### Source for first sample program

```
*****
** This is a sample assembler language program that is      *
** used with the TEST tutorial in the publication,          *
** TSO/E Programming Guide.                                *
**                                                         *
*****
SAMP1  CSECT
        STM 14,12,12(13)
        BALR 12,0
        USING *,12
        ST 13,SAVE+4
        LA 15,SAVE
        ST 15,8(13)
        LR 13,15
STOP1  LH 3,HALFCON
STOP2  A 3,FULLCON
STOP3  ST 3,HEXCON
        L 13,4(13)
        LM 14,12,12(13)
        BR 14
SAVE   DC 18F'0'
ADCON  DC A(SAVE)
FULLCON DC F'-1'
HEXCON DC XL4'FD38'
HALFCON DC H'32'
CHARCON DC CL10'TEST EXAMP'
PACKCON DC PL4'25'
BINCON DC B'10101100'
        END SAMP1
```

### Listing for first sample program

External Symbol Dictionary									
Symbol	Type	Id	Address	Length	Owner	Id	Flags	Alias-of	
SAMP1	SD	00000001	00000000	00000091			00		HLASM R6.0 2008/09/23 11.08

LOC	OBJECT CODE	ADDR1	ADDR2	STMT	SOURCE STATEMENT	
				1	*****	HLASM R6.0 2008/09/23 11.08
				2	**	*
				3	** This is a sample assembler language program that is	*
				4	** used with the TEST tutorial in the publication,	*
				5	** TSO/E Programming Guide.	*
				6	**	*

## Example programs for the TEST tutorial

```

000000          00000 00091      7 *****
000000 90EC D00C          0000C      8 SAMP1  CSECT
000004 05C0          R:C 00006      9          STM 14,12,12(13)
                                10          BALR 12,0
                                11          USING *,12
000006 50D0 C02A          00030      12          ST 13,SAVE+4
00000A 41F0 C026          0002C      13          LA 15,SAVE
00000E 50FD 0008          00008      14          ST 15,8(13)
000012 18DF          15          LR 13,15
000014 4830 C07A          00080      16 STOP1  LH 3,HALFCON
000018 5A30 C072          00078      17 STOP2  A 3,FULLCON
00001C 5030 C076          0007C      18 STOP3  ST 3,HEXCON
000020 58DD 0004          00004      19          L 13,4(13)
000024 98EC D00C          0000C      20          LM 14,12,12(13)
000028 07FE          21          BR 14
00002A 0000
00002C 0000000000000000      22 SAVE    DC 18F'0'
000074 0000002C      23 ADCON    DC A(SAVE)
000078 FFFFFFFF      24 FULLCON  DC F'-1'
00007C 0000FD38      25 HEXCON   DC XL4'FD38'
000080 0020      26 HALFCON  DC H'32'
000082 E3C5E2E340C5E7C1      27 CHARCON  DC CL10'TEST EXAMP'
00008C 0000025C      28 PACKCON  DC PL4'25'
000090 AC      29 BINCON    DC B'10101100'
000000          30          END  SAMP1
                                Relocation Dictionary
Pos.Id  Rel.Id  Address  Type  Action                                HLASM R6.0  2008/09/23 11.08
00000001 00000001 00000074  A 4  +
                                Ordinary Symbol and Literal Cross Reference
Symbol  Length  Value      Id  R Type Asm Program  Defn References  HLASM R6.0  2008/09/23 11.08
FULLCON  4  00000078  00000001  F  F          24 17
HALFCON  2  00000080  00000001  H  H          26 16
HEXCON   4  0000007C  00000001  X  X          25 18M
SAMP1    1  00000000  00000001  J          8 30
SAVE     4  0000002C  00000001  F  F          22 12M 13 23
                                Unreferenced Symbols Defined in CSECTs
Defn  Symbol                                HLASM R6.0  2008/09/23 11.08
23  ADCON
29  BINCON
27  CHARCON
28  PACKCON
16  STOP1
17  STOP2
18  STOP3

                                Using Map
Stmnt  -----Location----- Action -----Using----- Reg Max  Last Label and Using
Text
11  Count  Id  Type  Value  Range  Id  Disp  Stmnt
00000006 00000001 USING ORDINARY 00000006 00001000 00000001 12 0007A 18 *,12
                                General Purpose Register Cross Reference
Register  References (M=modified, B=branch, U=USING, D=DROP, N=index)  HLASM R6.0  2008/09/23 11.08
0(0)      9 20M
1(1)      9 20M
2(2)      9 20M
3(3)      9 16M 17M 18 20M
4(4)      9 20M
5(5)      9 20M
6(6)      9 20M
7(7)      9 20M
8(8)      9 20M
9(9)      9 20M
10(A)     9 20M
11(B)     9 20M
12(C)     9 10M 11U 20M
13(D)     9 12 14N 15M 19M 19N 20
14(E)     9 20M 21B
15(F)     9 13M 14 15 20M
                                Diagnostic Cross Reference and Assembler Summary
                                HLASM R6.0  2008/09/23 11.08
No Statements Flagged in this Assembly
HIGH LEVEL ASSEMBLER, 5696-234, RELEASE 6.0, PTF UK37157
SYSTEM: z/OS 01.10.00 JOBNAME: MKASPERN STEPNAME: SAMPLE1 PROCSTEP: (NOPROC)
Data Sets Allocated for this Assembly
Con DDname  Data Set Name  Volume  Member
P1 SYSIN    MKASPER.SAMPLE1.SAM  SL8D18
L1          SYS1.MODGEN  PRIPKR
L2          SYS1.MACLIB  PRIPKR
          SYSLIN  NULLFILE
          SYSPRINT SYS08267.T110803.RA000.MKASPERN.ASMPTT.H01  SMSSC5
          SYSPUNCH SYS08267.T110803.RA000.MKASPERN.OBJKEEP.H01

```

```

1533936K allocated to Buffer Pool      Storage required      228K
  30 Primary Input Records Read        0 Library Records Read      0 Work File Reads
  0 ASMAOPT Records Read              188 Primary Print Records Written 0 Work File Writes
  6 Object Records Written             0 ADATA Records Written
Assembly Start Time: 11.08.03 Stop Time: 11.08.03 Processor Time: 00.00.00.0004
Return Code 000

```

### Source for second sample program

```

*****
**                                     *
** This is a sample assembler language program that is *
** used with the TEST tutorial in the publication, *
** TSO/E Programming Guide. *
**                                     *
** NOTE: There is an error in this program. It is intended *
** to be located and fixed in the TEST tutorial. *
*****
TABAVG  CSECT
        STM 14,12,12(13)
        BALR 12,0
        USING *,12
        ST 13,SAVE+4
        LA 15,SAVE
        ST 15,8(13)
        LR 13,15
        OPEN (OUTDCB,(OUTPUT))
        L 7,TABSIZE
        SR 6,6
        SR 5,5
ADDIT   AH 5,TAB(6)
        LA 6,2(6)
        BCT 7,ADDIT
        ST 5,SUM
        SR 4,4
        DR 4,7
        STM 4,5,AVG
        PUT OUTDCB,OUTMSG
        CLOSE (OUTDCB)
        L 13,4(13)
        LM 14,12,12(13)
        BR 14
SAVE    DC 18F'0'
TABSIZE DC F'12'
AVG     DC 2F'0'
SUM     DC F'0'
TAB     DC H'31'
        DC H'29'
        DC H'31'
        DC H'30'
        DC H'31'
        DC H'30'
        DC H'31'
        DC H'30'
        DC H'31'
        DC H'30'
        DC H'31'
        DC H'30'
        DC H'31'
OUTMSG  DC CL50'TABLE AVERAGE PROGRAM
OUTDCB  DCB DDNAME=OUTDD,LRECL=50,BLKSIZE=50,RECFM=F,
        MACRF=(PM),DSORG=PS
        END  TABAVG

```

### Listing for second sample program

External Symbol Dictionary

## Example programs for the TEST tutorial

Symbol	Type	Id	Address	Length	Owner	Id	Flags	Alias-of	HLASM R6.0
2008/09/23	11.25								
TABAVG	SD	00000001	00000000	00000168			00		
LOC	OBJECT	CODE	ADDR1	ADDR2	STMT	SOURCE	STATEMENT		HLASM R6.0
2008/09/23	11.25								
					1	*****			
					2	**			*
					3	**	This is a sample assembler language program that is		*
					4	**	used with the TEST tutorial in the publication,		*
					5	**	TSO/E Programming Guide.		*
					6	**			*
					7	**	NOTE: There is an error in this program. It is intended		*
					8	**	to be located and fixed in the TEST tutorial.		*
					9	*****			
	000000		00000	00168	10	TABAVG			
	CSECT								
	000000	90EC	D00C		11		STM		
	14,12,12(13)			0000C					
	000004	05C0			12		BALR		
	12,0								
			R:C	00006	13		USING		
	*,12								
	000006	50D0	C062		14		ST	13,SAVE	
	+4			00068					
	00000A	41F0	C05E		15		LA		
	15,SAVE			00064					
	00000E	50FD	0008		16		ST		
	15,8(13)			00008					
	000012	18DF			17		LR		
	13,15								
					18		OPEN	(OUTDCB,	
	(OUTPUT))								
	000014				19+		CNOP	0,4	ALIGN LIST TO
	FULLWORD								
	000014	4510	C016		20+		BAL	1,++8	LOAD REG1 W/LIST
	ADDR. @L2A			0001C					
	000018	8F			21+		DC	AL1(143)	OPTION
	BYTE								
	000019	000108			22+		DC	AL3(OUTDCB)	DCB
	ADDRESS								
	00001C	0A13			23+		SVC	19	ISSUE OPEN
	SVC								
	00001E	5870	C0A6		24		L		
	7,TABSIZE			000AC					
	000022	1B66			25		SR		
	6,6								
	000024	1B55			26		SR		
	5,5								
	000026	4A56	C0B6		27	ADDIT	AH		
	5,TAB(6)			000BC					
	00002A	4166	0002		28		LA		
	6,2(6)			00002					
	00002E	4670	C020		29		BCT		
	7,ADDIT			00026					
	000032	5050	C0B2		30		ST		
	5,SUM			000B8					
	000036	1B44			31		SR		
	4,4								
	000038	1D47			32		DR		
	4,7								
	00003A	9045	C0AA		33		STM		
	4,5,AVG			000B0					
					34		PUT		
	OUTDCB,OUTMSG								
	00003E	4110	C102		36+		LA	1,OUTDCB	LOAD PARAMETER
	REG 1			00108					
	000042	4100	C0CE		37+		LA	0,OUTMSG	LOAD PARAMETER
	REG 0			000D4					
	000046	1FFF			38+		SLR	15,15	CLEAR
	REGISTER								
	000048	BFF7	1031		39+		ICM	15,7,49(1)	LOAD PUT ROUTINE
	ADDR @L1C			00031					
	00004C	05EF			40+		BALR	14,15	LINK TO PUT
	ROUTINE								
					41		CLOSE		
	(OUTDCB)								
	00004E	0700			42+		CNOP	0,4	ALIGN LIST TO
	FULLWORD								
	000050	4510	C052		43+		BAL	1,++8	LOAD REG1 W/LIST
	ADDR. @L2A			00058					
	000054	80			44+		DC	AL1(128)	OPTION



```

BYTE
000055 000108          45+      DC      AL3(OUTDCB)          DCB
ADDRESS
000058 0A14            46+      SVC      20                  ISSUE CLOSE
SVC
00005A 58DD 0004      00004    47      L
13,4(13)
00005E 98EC D00C      0000C    48      LM
14,12,12(13)
000062 07FE          49      BR
14
000064 0000000000000000 50 SAVE  DC
18F'0'
0000AC 0000000C      51 TABSIZE DC
F'12'
0000B0 0000000000000000 52 AVG   DC
2F'0'
0000B8 00000000      53 SUM     DC
F'0'
0000BC 001F          54 TAB     DC
H'31'
0000BE 001D          55      DC
H'29'
0000C0 001F          56      DC      H'31'

LOC OBJECT CODE ADDR1 ADDR2 STMT SOURCE STATEMENT
0000C2 001E          57      DC
H'30'
0000C4 001F          58      DC
H'31'
0000C6 001E          59      DC
H'30'
0000C8 001F          60      DC
H'31'
0000CA 001F          61      DC
H'31'
0000CC 001E          62      DC
H'30'
0000CE 001F          63      DC
H'31'
0000D0 001E          64      DC
H'30'
0000D2 001F          65      DC
H'31'
0000D4 E3C1C2D3C540C1E5 66 OUTMSG DC CL50'TABLE AVERAGE
PROGRAM
0000D6 001F          67 OUTDCB DCB
DDNAME=OUTDD,LRECL=50,BLKSIZE=50,RECFM=F,
MACRF=(PM),DSORG=PS
70+* DATA CONTROL BLOCK
71+*
000106 0000          72+OUTDCB DC 0F'0' ORIGIN ON WORD
000108
BOUNDARY
000108 0000000000000000 73+* DIRECT ACCESS DEVICE INTERFACE
DVTBL 74+ DC BL16'0' FDAD,
000118 00000000      75+ DC A(0) KEYLEN, DEVT,
TRBAL
00011C 00          76+* COMMON ACCESS METHOD INTERFACE
BUFFERS 77+ DC AL1(0) BUFNO, NUMBER OF
00011D 000001      78+ DC AL3(1) BUFCB, BUFFER POOL CONTROL
BLOCK
000120 0000      79+ DC AL2(0) BUFL, BUFFER
LENGTH
000122 4000      80+ DC BL2'0100000000000000' DSORG, DATA SET
ORGANIZATION
000124 00000001      81+ DC A(1) IOBAD FOR EXCP OR
RESERVED
000128 00          82+* FOUNDATION EXTENSION
INDICATORS 83+ DC BL1'00000000' BFTEK, BFALN, DCBE
000129 000001      84+ DC AL3(1) EODAD (END OF DATA ROUTINE
ADDRESS)
00012C 80          85+ DC BL1'10000000' RECFM (RECORD
FORMAT)
00012D 000000      86+ DC AL3(0) EXLST (EXIT LIST
ADDRESS)
000130 D6E4E3C4C4404040 87+* FOUNDATION BLOCK
88+ DC CL8'OUTDD'

```

## Example programs for the TEST tutorial

```

DDNAME
000138 02          89+      DC    BL1'00000010'  OFLGS (OPEN
FLAGS)
000139 00          90+      DC    BL1'00000000'  IFLGS (IOS
FLAGS)
00013A 0050        91+      DC    BL2'0000000001010000' MACR (MACRO
FORMAT)
                                92+*      BSAM-BPAM-QSAM INTERFACE
00013C 00          93+      DC    BL1'00000000'  OPTCD, OPTION
CODES
00013D 000001      94+      DC    AL3(1)          CHECK OR INTERNAL QSAM
SYNCHRONIZING RTN.
000140 00000001    95+      DC    A(1)            SYNAD, SYNCHRONOUS ERROR RTN. (3
BYTES)
000144 0000        96+      DC    H'0'            INTERNAL ACCESS METHOD
FLAGS
000146 0032        97+      DC    AL2(50)         BLKSIZE, BLOCK
SIZE
000148 00000000    98+      DC    F'0'            INTERNAL ACCESS METHOD
FLAGS
00014C 00000001    99+      DC    A(1)            INTERNAL ACCESS METHOD
USE
                                100+*     QSAM INTERFACE
000150 00000001    101+     DC    A(1)
EOBAD
000154 00000001    102+     DC    A(1)
RECAD
000158 0000        103+     DC    H'0'            QSWs (FLAGS) AND EITHER DIRCT OR
BUFOFF
00015A 0032        104+     DC    AL2(50)
LRECL
00015C 00          105+     DC    BL1'00000000'  EROPT, ERROR
OPTION
00015D 000001      106+     DC    AL3(1)
CNTRL
000160 00000000    107+     DC    H'0,0'          RESERVED AND
PRECL
000164 00000001    108+     DC    A(1)            EOB, INTERNAL ACCESS METHOD
FIELD
000000            109      END
TAVAVG

                                Relocation Dictionary
                                HLASM R6.0
Pos.Id  Rel.Id  Address  Type  Action
2008/09/23 11.25
00000001 00000001 00000019  A 3    +
00000001 00000001 00000055  A 3    +
                                Ordinary Symbol and Literal Cross Reference
Symbol    Length  Value      Id    R Type Asm  Program  Defn References
2008/09/23 11.25
ADDIT      4 00000026 00000001    I          27 29B
AVG         4 000000B0 00000001    F F        52 33M
OUTDCB     4 00000108 00000001    F F        72 22    36    45
OUTMSG     50 000000D4 00000001    C C        66 37
SAVE       4 00000064 00000001    F F        50 14M    15
SUM        4 000000B8 00000001    F F        53 30M
TAB        2 000000BC 00000001    H H        54 27
TAVAVG     1 00000000 00000001    J          10 109
TABSIZ     4 000000AC 00000001    F F        51 24
                                Using Map
                                HLASM R6.0
2008/09/23 11.25
Stmnt  -----Location----- Action -----Using----- Reg Max  Last Label and Using
Text
Count    Id    Type    Value    Range    Id    Disp  Stmnt
13 00000006 00000001 USING ORDINARY 00000006 00001000 00000001 12 00102 43 *,12
                                General Purpose Register Cross Reference
Register  References (M=modified, B=branch, U=USING, D=DROP, N=index)
2008/09/23 11.25
0(0)      11    37M    48M
1(1)      11    20M    36M    39    43M    48M
2(2)      11    48M
3(3)      11    48M
4(4)      11    31M    31    32M    33    48M
5(5)      11    26M    26    27M    30    32M    33    48M
6(6)      11    25M    25    27N    28M    28N    48M
7(7)      11    24M    29M    32    48M
8(8)      11    48M
9(9)      11    48M
10(A)     11    48M
11(B)     11    48M
12(C)     11    12M    13U    48M
13(D)     11    14     16N    17M    47M    47N    48

```

```

14(E)      11      40M      48M      49B
15(F)      11      15M      16       17      38M      38      39M      40B      48M
Diagnostic Cross Reference and Assembler Summary
HLASM R6.0

2008/09/23 11.25
No Statements Flagged in this Assembly
HIGH LEVEL ASSEMBLER, 5696-234, RELEASE 6.0, PTF UK37157
SYSTEM: z/OS 01.10.00      JOBNAME: MKASPERO      STEPNAME: SAMPLE2      PROCSTEP: (NOPROC)
Data Sets Allocated for this Assembly
Con DDname      Data Set Name      Volume      Member
P1 SYSIN        MKASPER.SAMPLE2.SAM      SL6294
L1              SYS1.MODGEN              PRIPKR
L2              SYS1.MACLIB              PRIPKR
SYSLIN          NULLFILE
SYSPRINT        SYS08267.T112528.RA000.MKASPER0.ASMPT.H01      SMSSC4
SYSPUNCH        SYS08267.T112528.RA000.MKASPER0.OBJKEEP.H01

1533756K allocated to Buffer Pool      Storage required      500K
 53 Primary Input Records Read      2675 Library Records Read      0 Work File Reads
 0 ASMAOPT Records Read      268 Primary Print Records Written      0 Work File Writes
10 Object Records Written      0 ADATA Records Written
Assembly Start Time: 11.25.29 Stop Time: 11.25.29 Processor Time: 00.00.00.0116
Return Code 000

```



---

## Appendix A. Accessibility

Accessible publications for this product are offered through [IBM Knowledge Center \(www.ibm.com/support/knowledgecenter/SSLTBW/welcome\)](http://www.ibm.com/support/knowledgecenter/SSLTBW/welcome).

If you experience difficulty with the accessibility of any z/OS information, send a detailed email message to [mhvrcfs@us.ibm.com](mailto:mhvrcfs@us.ibm.com).

---

### Accessibility features

Accessibility features help users who have physical disabilities such as restricted mobility or limited vision use software products successfully. The accessibility features in z/OS can help users do the following tasks:

- Run assistive technology such as screen readers and screen magnifier software.
- Operate specific or equivalent features by using the keyboard.
- Customize display attributes such as color, contrast, and font size.

---

### Consult assistive technologies

Assistive technology products such as screen readers function with the user interfaces found in z/OS. Consult the product information for the specific assistive technology product that is used to access z/OS interfaces.

---

### Keyboard navigation of the user interface

You can access z/OS user interfaces with TSO/E or ISPF. The following information describes how to use TSO/E and ISPF, including the use of keyboard shortcuts and function keys (PF keys). Each guide includes the default settings for the PF keys.

- [\*z/OS TSO/E Primer\*](#)
- [\*z/OS TSO/E User's Guide\*](#)
- [\*z/OS ISPF User's Guide Vol I\*](#)

---

### Dotted decimal syntax diagrams

Syntax diagrams are provided in dotted decimal format for users who access IBM Knowledge Center with a screen reader. In dotted decimal format, each syntax element is written on a separate line. If two or more syntax elements are always present together (or always absent together), they can appear on the same line because they are considered a single compound syntax element.

Each line starts with a dotted decimal number; for example, 3 or 3.1 or 3.1.1. To hear these numbers correctly, make sure that the screen reader is set to read out punctuation. All the syntax elements that have the same dotted decimal number (for example, all the syntax elements that have the number 3.1) are mutually exclusive alternatives. If you hear the lines 3.1 USERID and 3.1 SYSTEMID, your syntax can include either USERID or SYSTEMID, but not both.

The dotted decimal numbering level denotes the level of nesting. For example, if a syntax element with dotted decimal number 3 is followed by a series of syntax elements with dotted decimal number 3.1, all the syntax elements numbered 3.1 are subordinate to the syntax element numbered 3.

Certain words and symbols are used next to the dotted decimal numbers to add information about the syntax elements. Occasionally, these words and symbols might occur at the beginning of the element itself. For ease of identification, if the word or symbol is a part of the syntax element, it is preceded by the backslash (\) character. The \* symbol is placed next to a dotted decimal number to indicate that the syntax element repeats. For example, syntax element \*FILE with dotted decimal number 3 is given the format 3 \\* FILE. Format 3\* FILE indicates that syntax element FILE repeats. Format 3\* \\* FILE indicates that syntax element \* FILE repeats.

Characters such as commas, which are used to separate a string of syntax elements, are shown in the syntax just before the items they separate. These characters can appear on the same line as each item, or on a separate line with the same dotted decimal number as the relevant items. The line can also show another symbol to provide information about the syntax elements. For example, the lines 5.1\*, 5.1 LASTRUN, and 5.1 DELETE mean that if you use more than one of the LASTRUN and DELETE syntax elements, the elements must be separated by a comma. If no separator is given, assume that you use a blank to separate each syntax element.

If a syntax element is preceded by the % symbol, it indicates a reference that is defined elsewhere. The string that follows the % symbol is the name of a syntax fragment rather than a literal. For example, the line 2.1 %OP1 means that you must refer to separate syntax fragment OP1.

The following symbols are used next to the dotted decimal numbers.

#### **? indicates an optional syntax element**

The question mark (?) symbol indicates an optional syntax element. A dotted decimal number followed by the question mark symbol (?) indicates that all the syntax elements with a corresponding dotted decimal number, and any subordinate syntax elements, are optional. If there is only one syntax element with a dotted decimal number, the ? symbol is displayed on the same line as the syntax element, (for example 5? NOTIFY). If there is more than one syntax element with a dotted decimal number, the ? symbol is displayed on a line by itself, followed by the syntax elements that are optional. For example, if you hear the lines 5 ?, 5 NOTIFY, and 5 UPDATE, you know that the syntax elements NOTIFY and UPDATE are optional. That is, you can choose one or none of them. The ? symbol is equivalent to a bypass line in a railroad diagram.

#### **! indicates a default syntax element**

The exclamation mark (!) symbol indicates a default syntax element. A dotted decimal number followed by the ! symbol and a syntax element indicate that the syntax element is the default option for all syntax elements that share the same dotted decimal number. Only one of the syntax elements that share the dotted decimal number can specify the ! symbol. For example, if you hear the lines 2? FILE, 2.1! (KEEP), and 2.1 (DELETE), you know that (KEEP) is the default option for the FILE keyword. In the example, if you include the FILE keyword, but do not specify an option, the default option KEEP is applied. A default option also applies to the next higher dotted decimal number. In this example, if the FILE keyword is omitted, the default FILE (KEEP) is used. However, if you hear the lines 2? FILE, 2.1, 2.1.1! (KEEP), and 2.1.1 (DELETE), the default option KEEP applies only to the next higher dotted decimal number, 2.1 (which does not have an associated keyword), and does not apply to 2? FILE. Nothing is used if the keyword FILE is omitted.

#### **\* indicates an optional syntax element that is repeatable**

The asterisk or glyph (\*) symbol indicates a syntax element that can be repeated zero or more times. A dotted decimal number followed by the \* symbol indicates that this syntax element can be used zero or more times; that is, it is optional and can be repeated. For example, if you hear the line 5.1\* data area, you know that you can include one data area, more than one data area, or no data area. If you hear the lines 3\* , 3 HOST, 3 STATE, you know that you can include HOST, STATE, both together, or nothing.

#### **Notes:**

1. If a dotted decimal number has an asterisk (\*) next to it and there is only one item with that dotted decimal number, you can repeat that same item more than once.
2. If a dotted decimal number has an asterisk next to it and several items have that dotted decimal number, you can use more than one item from the list, but you cannot use the items more than once each. In the previous example, you can write HOST STATE, but you cannot write HOST HOST.

3. The \* symbol is equivalent to a loopback line in a railroad syntax diagram.

**+ indicates a syntax element that must be included**

The plus (+) symbol indicates a syntax element that must be included at least once. A dotted decimal number followed by the + symbol indicates that the syntax element must be included one or more times. That is, it must be included at least once and can be repeated. For example, if you hear the line 6.1+ data area, you must include at least one data area. If you hear the lines 2+, 2 HOST, and 2 STATE, you know that you must include HOST, STATE, or both. Similar to the \* symbol, the + symbol can repeat a particular item if it is the only item with that dotted decimal number. The + symbol, like the \* symbol, is equivalent to a loopback line in a railroad syntax diagram.





## Notices

---

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
United States of America*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan*

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for the Knowledge Centers. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Corporation  
Site Counsel  
2455 South Road*

Poughkeepsie, NY 12601-5400  
USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### **COPYRIGHT LICENSE:**

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

## **Terms and conditions for product documentation**

---

Permissions for the use of these publications are granted subject to the following terms and conditions.

### **Applicability**

These terms and conditions are in addition to any terms of use for the IBM website.

### **Personal use**

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

### **Commercial use**

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

## **Rights**

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

## **IBM Online Privacy Statement**

---

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at [ibm.com/privacy](http://ibm.com/privacy) and IBM's Online Privacy Statement at [ibm.com/privacy/details](http://ibm.com/privacy/details) in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at [ibm.com/software/info/product-privacy](http://ibm.com/software/info/product-privacy).

## **Policy for unsupported hardware**

---

Various z/OS elements, such as DFSMS, JES2, JES3, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

## Minimum supported hardware

---

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: [IBM Lifecycle Support for z/OS \(www.ibm.com/software/support/systemsz/lifecycle\)](http://www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

## Trademarks

---

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at [Copyright and Trademark information \(www.ibm.com/legal/copytrade.shtml\)](http://www.ibm.com/legal/copytrade.shtml).

---

# Index

## Special Characters

- ? indirection symbol
  - 31-bit addressing considerations for TEST [92](#)
  - 31-bit addressing considerations for TESTAUTH [92](#)
- % indirection symbol [88](#)
- <TSO/E>
  - summary of changes [xvi](#)

## Numerics

- 31-bit addressing considerations for TEST [92](#)
- 31-bit addressing considerations for TESTAUTH [92](#)

## A

- abend
  - completion code [42](#)
  - ESTAE/ESTAI relationship [41](#)
- absolute address [86](#)
- access register [88](#)
- access to storage by TEST and TESTAUTH
  - setting breakpoints
    - for cross-memory applications [93](#)
- accessibility
  - contact IBM [133](#)
  - features [133](#)
- addressing considerations under TEST and TESTAUTH [91](#)
- alternative library interface routine (IKJADTAB) [8](#)
- application invocation function (ICQAMLIO) [9](#)
- ASM command [67](#)
- assembling a program [67](#)
- assignment function of TEST [111](#)
- assistive technologies [133](#)
- AT subcommand of TEST [108](#)
- ATTACH macro [40](#)
- attention exit handling routine
  - attention exit parameter list (AEPL) [50](#)
  - command processor use of [47](#)
  - full-screen protection responsibility [50](#)
  - parameter received by [48](#)
  - register content at entry [49](#)
  - scheduling [46](#)
- attention interruption handling (STAX) [45](#)
- automatic qualification [86](#)

## B

- binder listing
  - producing for control statements [73](#)
- breakpoint [79](#), [108](#)

## C

- CALL command
  - example [77](#), [78](#)

- CALL command (*continued*)
  - loading and executing a load module [77](#)
  - passing a parameter when loading and executing load modules [78](#)
- CALL subcommand of TEST [121](#)
- CALLTSSR macro instruction [8](#)
- catalog information routine (IKJEHCIR) [9](#)
- changing the source of input
  - STACK service routine [29](#)
- checking syntax
  - of a command operand [19](#)
  - of subcommand operand [39](#)
- CLIST
  - advantage of [5](#)
  - file compression restrictions [6](#)
- CLIST attention facility (IKJCAF) [8](#), [45](#)
- COBOL command [67](#)
- command buffer
  - format of [14](#)
  - input to command scan service routine (IKJSCAN) [39](#)
  - input to parse service routine (IKJPARS) [19](#)
  - returned by PUTGET [39](#)
- command library
  - adding a new member [57](#)
  - concatenating a new data set [57](#)
- command operand
  - checking syntax of [19](#)
  - determining validity of [19](#)
  - keyword operand [15](#)
  - positional operand [15](#)
  - subfield of a keyword operand [15](#)
- command processor
  - adding to private step library [57](#)
  - adding to SYS1.CMDLIB [57](#)
  - advantage of [5](#)
  - attention exit routine [47](#)
  - changing the source of input [29](#)
  - communicating with the terminal user [27](#)
  - completion code [42](#)
  - definition of [11](#)
  - determining validity of an operand [19](#)
  - example [22](#)
  - executing [59](#)
  - full-screen processing [29](#)
  - function that relies on error routine support [41](#)
  - giving control to [31](#)
  - installing [57](#)
  - message handling [27](#)
  - passing control to a subcommand processor [39](#)
  - processing an abnormal termination (abend) [41](#)
  - processing attention interruption [45](#)
  - resetting input stack after an attention interruption [48](#)
  - return code [17](#)
  - steps for writing [17](#)
  - termination of full-screen [33](#)
  - testing [59](#)
- command processor parameter list

- command processor parameter list (*continued*)
  - (CPPL) [13](#)
  - mapping macro [17](#)
- command processor parameter list (CPPL)
  - accessing [17](#)
- command scan service routine (IKJSCAN) [39](#)
- Command scan service routine (IKJSCAN) [8](#)
- commands
  - ASM command [67](#)
  - CALL command [77](#)
  - COBOL command [67](#)
  - FORT command [67](#)
  - HELP command [51](#)
  - information about (HELP) [51](#)
  - LINK command [71](#)
  - LOADGO command [75](#)
  - PLI command [67](#)
  - RUN command [68](#)
  - TEST command [79](#)
  - TESTAUTH command [79](#)
- communicating with the user at the terminal [27](#)
- compiling a program [67](#)
- compression
  - control for REXX execs [6](#)
- concatenating HELP data sets [51](#)
- contact
  - z/OS [133](#)
- control statements
  - producing a listing [73](#)
- controlling REXX exec compression [6](#)
- COPY subcommand of TEST [111](#)
- CP or NOCP (operand of TEST and TESTAUTH) [81](#)
- CPPL (command processor parameter list) [13](#)
- creating HELP information [51](#)
- cross-memory considerations for TEST and TESTAUTH [93](#)

## D

- DAIR (dynamic allocation interface routine) [8](#)
- DAIRFAIL routine (IKJEFF18) [9](#), [28](#)
- default service routine (IKJEHDEF) [9](#)
- DELETE subcommand of TEST [121](#)
- determining the validity of a command [19](#)
- diagnostic error message [42](#)
- DROP subcommand of TEST [117](#)
- Dumps
  - obtaining [80](#)

## E

- END subcommand of TEST [100](#)
- EQUATE subcommand of TEST [117](#)
- error message [42](#)
- ESTAE and ESTAI exit routine guidelines [42](#)
- ESTAE retry routine [43](#)
- example
  - full-screen command processor operation [33](#)
- example programs
  - first sample
    - source [125](#)
  - second sample
    - listing [127](#)
    - source [127](#)

- example programs (*continued*)
  - TEST tutorial [125](#)
- EXEC statement of LOGON procedures [13](#)
- exec, REXX [3](#)
- executing
  - comparing execution commands [63](#)
  - using the CALL command [77](#)
  - using the LOADGO command [75](#)
  - using the RUN command [68](#)
- executing a program
  - under control of TEST [80](#)
  - under control of TESTAUTH [80](#)
- exiting full-screen mode [32](#)
- external function, invoking considerations [32](#)

## F

- feedback [xv](#)
- floating-point register [87](#)
- format
  - of a HELP data set [52](#)
  - of HELP members [52](#)
- FORT command [67](#)
- FREEMAIN subcommand of TEST [120](#)
- full-screen
  - command processor
    - example of operation [33](#)
    - macro used [29](#)
    - termination [33](#)
  - mode
    - exiting [32](#)
    - reentering [32](#)
  - protection responsibility of attention exit [50](#)
- function
  - of INITIAL=NO [37](#)
  - of INITIAL=YES
    - when first message is full-screen [35](#)
    - when first message is non-full-screen [35](#), [36](#)
  - of reshown in full-screen message processing [34](#)

## G

- general register [87](#)
- GETMAIN subcommand of TEST [120](#)
- GETMSG. [9](#)
- GNRLFAIL/VSAMFAIL routine (IKJEFF19) [9](#), [28](#)
- GO subcommand of TEST [100](#)
- guidelines for ESTAE and ESTAI exit routines [42](#)

## H

- HELP data set
  - adding members to [52](#)
  - attributes of [51](#)
  - concatinating [51](#)
  - definition of [51](#)
  - format of [52](#)
  - updating [52](#)
- HELP information, creating [51](#)
- HELP subcommand of TEST [100](#)

## I

I/O service routine [8](#), [27](#)  
ICQCAL00 [9](#)  
ICQGCL00 [8](#)  
IKJEFF02 (TSO/E message issuer service routine) [28](#)  
IKJEFF18 (DAIRFAIL routine) [28](#)  
IKJEFF19 (GNRLFAIL/VSAMFAIL routine) [28](#)  
IKJPARS (parse service routine) [19](#)  
IKJSCAN [39](#)  
indirect address  
    ? (question mark) [88](#)  
    % (percent sign) [88](#)  
    definition and use [88](#)  
    example of indirect addressing [88](#)  
information about commands (HELP) [51](#)  
informational message, issuing [27](#)  
input buffer [39](#)

## K

keyboard  
    navigation [133](#)  
    PF keys [133](#)  
    shortcut keys [133](#)  
keyword operand [15](#)

## L

level of a message [27](#)  
LINK command  
    creating a load module [71](#)  
    creating a map of the load module [73](#)  
    example [71–74](#)  
    LIB [72](#)  
    LOAD [72](#)  
    NOLIST [73](#)  
    NOMAP [73](#)  
    NOPRINT [73](#)  
    NOTEST [74](#)  
    operand [71–74](#)  
    PRINT [73](#)  
    producing a cross reference table [74](#)  
    producing a list of all linkage editor control statements [73](#)  
    producing a symbol table [74](#)  
    producing an output listing [72](#)  
    resolving an external reference [72](#)  
    sending an error message to your terminal [74](#)  
    TEST [74](#)  
    XREF [74](#)  
link-editing a program [71](#)  
LIST subcommand of TEST [100](#), [121](#)  
LISTDCB subcommand of TEST [116](#)  
LISTDEB subcommand of TEST [117](#)  
listing  
    TEST tutorial [125](#), [127](#)  
LISTMAP subcommand of TEST [115](#)  
LISTPSW subcommand of TEST [116](#)  
LISTTCB subcommand of TEST [118](#)  
LISTVPS subcommand of TEST [122](#)  
LISTVSR subcommand of TEST [122](#)  
LOAD subcommand of TEST [121](#)

LOADGO command

    CALL [76](#)  
    EP [77](#)  
    example [75–77](#)  
    loading and executing programs with no operands [75](#)  
    MAP [77](#)  
    NOMAP [77](#)  
    operand [75–77](#)  
    passing a parameter [76](#)  
    passing a parameter when loading and executing programs [76](#)  
    PRINT [76](#)  
    producing an output listing [76](#)  
    program [76](#), [77](#)  
    requesting an output listing when loading and executing programs [76](#)  
    resolving an external reference [76](#)  
    resolving an external reference when loading and executing programs [76](#)  
    specifying a name when loading and executing programs [77](#)  
    specifying a program name [77](#)  
    specifying an entry point [77](#)  
    specifying an entry point when loading and executing programs [77](#)  
    specifying data-set-list [76](#)  
    TERM [76](#)  
loading a program [75](#)  
logon cataloged procedure  
    EXEC statement [13](#)

## M

macro instruction  
    GETLINE [28](#)  
    IKJUNFLD [20](#)  
    parse [19](#)  
    PUTLINE [28](#)  
    STACK [29](#)  
    STAX [45](#)  
    TGET [28](#)  
    TPG [28](#)  
    TPUT [28](#)  
    used to write a full-screen command processor [29](#)  
macro interface  
    ATTACH [43](#)  
    ESTAE [43](#)  
    FESTAE [43](#)  
message  
    class  
        definition [27](#)  
    error [42](#)  
    informational (issuing) [27](#)  
    level [27](#)  
    mode (definition) [27](#)  
    mode (issuing) [27](#), [39](#)  
    prompting (definition) [27](#)  
    prompting (issuing) [27](#)  
message handling  
    DAIRFAIL routine (IKJEFF18) [28](#)  
    GNRLFAIL/VSAMFAIL routine (IKJEFF19) [28](#)  
    I/O service routine [27](#)  
    message level [27](#)  
    TSO/E message issuer service routine (IKJEFF02) [28](#)

mode message  
  definition [27](#)  
  issuing [27](#), [39](#)  
module name [86](#)

## N

navigation  
  keyboard [133](#)  
NOCP or CP (operand of TEST and TESTAUTH) [81](#)  
NOEDIT mode [31](#)

## O

OFF subcommand of TEST [108](#)

## P

parameter  
  passed to attention handling routine [48](#)  
  received by attention handling routine [48](#)  
parameter list  
  attention exit parameter list (AEPL) [50](#)  
  command processor parameter list (CPPL) [13](#)  
parse service routine (IKJPARS)  
  prompt mode HELP [21](#)  
  validity checking routine [20](#)  
  verify exit routine [20](#)  
PLI command [67](#)  
positional operand  
  checking for logical error [20](#)  
printer support CLIST [9](#)  
program  
  assembling [67](#)  
  CLIST  
    advantage of [5](#)  
  command processor  
    advantage of [5](#)  
  compiling [67](#)  
  executing [63](#)  
  executing under TEST [80](#)  
  executing under TESTAUTH [80](#)  
  link-editing [71](#)  
  REXX exec  
    advantage of [5](#)  
  server [8](#)  
  testing authorized [79](#)  
  testing unauthorized [79](#)  
  type  
    CLIST [4](#)  
    command processor [4](#)  
    REXX exec [3](#)  
    server [8](#)  
program object  
  creating [71](#)  
  creating a map [73](#)  
programming services overview [8](#)  
prompt mode HELP  
  definition of [21](#)  
prompt mode HELP function  
  importance of ECTNOQPR bit [21](#)  
  making active for subcommands [21](#)  
  restriction on [21](#)

prompt mode HELP function (*continued*)  
  updating HELP members for [54](#)  
prompting message  
  definition [27](#)  
  issuing [27](#)  
protection of screen content [32](#)  
PUTGET service routine  
  processing a second-level message [28](#)  
PUTLINE service routine  
  processing a second-level message [28](#)

## Q

qualified address [86](#)  
QUALIFY subcommand of TEST [120](#)

## R

reading information from the terminal [31](#)  
reentering full-screen mode [32](#)  
register  
  access [88](#)  
  floating-point [87](#)  
  general [87](#)  
  vector [87](#)  
  vector mask [88](#)  
relative address [86](#)  
RESHOW [32](#), [33](#)  
restoration of screen content [32](#)  
retrieving information about commands and subcommands [51](#)  
return code from a command processor [17](#)  
REXX exec  
  advantage of [5](#)  
REXX exec compression [6](#)  
RUN command  
  compiling a source code statement [68](#)  
  passing a parameter when compiling [68](#)  
  specifying a subroutine library when compiling [69](#)  
  specifying a VS BASIC compiler option [69](#)

## S

sample programs  
  first sample  
    listing [125](#)  
screen content  
  protection [32](#)  
  restoration of [32](#)  
second-level message  
  definition [27](#)  
  requesting [27](#)  
sending to IBM  
  reader comments [xv](#)  
server [8](#)  
service provided by TSO/E [8](#)  
set full-screen mode on [31](#)  
SETVSR subcommand of TEST [122](#)  
shortcut keys [133](#)  
source code  
  TEST tutorial [125](#), [127](#)  
space management [8](#)  
STAX service routine



## STAX service routine (*continued*)

- CLIST attention exit [45](#)
- deferring attention exit [46](#)
- STFSMODE [30](#), [31](#)
- STLINENO [30](#)
- STTMPMD [30](#)
- subcommand
  - invoking [16](#)
  - recognizing [39](#)
- subcommand name
  - checking syntax of [39](#)
  - determining validity of [39](#)
- subcommand processor
  - definition of [16](#)
  - passing control to [40](#)
  - releasing [40](#)
  - steps for writing [40](#)
- subfield of a keyword operand [15](#)
- subpool [78](#) [40](#)
- summary of changes
  - <TSO/E> [xvi](#)
- Summary of changes [xvi](#)
- symbol
  - external [90](#)
  - internal [91](#)
  - restrictions [90](#)
- symbolic address [86](#)
- syntax notation conventions [9](#)

## T

- table look-up service (IKJTBL) [9](#)
- terminal attention interruption element (TAIE) [50](#)
- TERMINAL BREAK, use of [31](#)
- terminal control macro instructions [8](#)
- terminal I/O
  - BSAM [28](#)
  - GETLINE [28](#)
  - PUTLINE [28](#)
  - QSAM [28](#)
  - TGET [28](#)
  - TPG [28](#)
  - TPUT [28](#)
- TEST command
  - abend occurrences outside home address space [93](#)
  - access to storage [93](#)
  - addressing considerations [91](#)
  - addressing conventions [85](#)
  - command processor [81](#)
  - CP or NOCP operand [81](#)
  - cross-memory considerations [93](#)
  - definition of address expression [89](#)
  - description [79](#)
  - examples using TEST [82](#)
  - executing a program under control of [80](#)
  - extended addressing [94](#)
  - NOCP or CP operand [81](#)
  - program environment after testing [95](#)
  - restrictions on internal and external symbols [90](#)
  - setting breakpoints
    - for cross-memory applications [93](#)
  - testing a command processor [59](#)
  - testing a program [79](#), [80](#), [82](#), [85](#), [89–91](#), [93–95](#), [108](#)
  - tutorial [97](#)

## TEST command (*continued*)

- types of addresses [85](#)
- using virtual fetch services [93](#)
- valid address examples [91](#)
- vector facility [93](#)
- when to use [80](#)
- TEST subcommand
  - list of [84](#)
  - used in tutorial
    - assignment function (=) [111](#)
    - AT [108](#)
    - CALL [121](#)
    - COPY [111](#)
    - DELETE [121](#)
    - DROP [117](#)
    - END [100](#)
    - EQUATE [117](#)
    - FREEMAIN [120](#)
    - GETMAIN [120](#)
    - GO [100](#)
    - HELP [100](#)
    - LIST [100](#), [121](#)
    - LISTDCB [116](#)
    - LISTDEB [117](#)
    - LISTMAP [115](#)
    - LISTPSW [116](#)
    - LISTTCB [118](#)
    - LISTVP [122](#)
    - LISTVSR [122](#)
    - LOAD [121](#)
    - OFF [108](#)
    - QUALIFY [120](#)
    - SETVSR [122](#)
    - WHERE [106](#)
- TEST tutorial
  - example programs [125](#)
- TESTAUTH command
  - abend occurrences outside home address space [93](#)
  - access to storage [93](#)
  - addressing considerations [91](#)
  - addressing conventions [85](#)
  - CP or NOCP operand [81](#)
  - cross-memory considerations [93](#)
  - definition of address expression [89](#)
  - description [79](#)
  - examples using TESTAUTH [82](#)
  - executing a program under control of [80](#)
  - extended addressing [94](#)
  - NOCP or CP operand [81](#)
  - program environment after testing [95](#)
  - restrictions on internal and external symbols [90](#)
  - setting breakpoints
    - for cross-memory applications [93](#)
  - testing a command processor [81](#)
  - testing a program [79](#), [80](#), [82](#), [85](#), [89–91](#), [93–95](#)
  - types of addresses [85](#)
  - using virtual fetch services [93](#)
  - valid address examples [91](#)
  - vector facility [93](#)
  - when to use [80](#)
- TESTAUTH subcommand [84](#)
- testing a command processor [59](#)
- TGET [30](#), [31](#)
- TGET ASIS [31](#)

TPG [31](#)  
TPUT [30](#), [31](#)  
TPUT FULLSCR [31](#)  
TPUT NOEDIT [31](#)  
trademarks [140](#)  
TSO/E message issuer service routine (IKJEFF02) [28](#)  
TSO/E service facility (IKJEFTSR) [9](#), [17](#)

## U

updating SYS1.HELP [52](#)  
UPT (user profile table)  
    description [14](#)  
user interface  
    ISPF [133](#)  
    TSO/E [133](#)  
user profile table  
    accessing [14](#)  
user, communicating with [27](#)

## V

validity checking routine [20](#)  
vector mask register [88](#)  
vector register [87](#)  
verify exit routine [20](#)  
virtual fetch service [93](#)  
VTAM full-screen mode [29](#)

## W

WHERE subcommand of TEST [106](#)  
writing HELP members [52](#)  
writing information to the terminal [31](#)





SA32-0981-30

