

High Level Assembler for z/OS & z/VM & z/VSE



# Programmer's Guide

*Release 6*



High Level Assembler for z/OS & z/VM & z/VSE



# Programmer's Guide

*Release 6*

**Note!**

Before using this information and the product it supports, be sure to read the general information under "Notices" on page 441.

**Sixth Edition (July 2008)**

This edition applies to IBM High Level Assembler for z/OS & z/VM & z/VSE, Release 6, Program Number 5696-234 and to any subsequent releases until otherwise indicated in new editions. Make sure you are using the correct edition for the level of the product.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

A form for reader's comments is provided at the back of this publication. If the form has been removed, address your comments to:

IBM Corporation  
Reader Comments  
DTX/E269  
555 Bailey Avenue  
SAN JOSE, CA 95141-1003  
U.S.A.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1982, 2008. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>About this document . . . . .</b>	<b>ix</b>
Who should use this document . . . . .	ix
Programming interface information . . . . .	ix
Organization of this document . . . . .	x
IBM High Level Assembler for z/OS & z/VM & z/VSE Publications . . . . .	xi
Hardcopy Publications . . . . .	xi
Online publications . . . . .	xiii
Related publications . . . . .	xiii
Syntax notation . . . . .	xiii

<b>Summary of changes . . . . .</b>	<b>xvii</b>
-------------------------------------	-------------

---

## Part 1. Understanding and using the assembler . . . . . 1

### Chapter 1. Introduction . . . . . 3

Requirements . . . . .	3
System requirements . . . . .	3
Machine requirements . . . . .	3
Storage requirements . . . . .	4
Compatibility . . . . .	4
Assembler language support . . . . .	4
Migration considerations . . . . .	5

### Chapter 2. Using the assembler listing . 7

High Level Assembler option summary . . . . .	8
External Symbol Dictionary (ESD) . . . . .	11
Source and object . . . . .	14
Relocation dictionary (RLD) . . . . .	21
Ordinary symbol and literal cross reference . . . . .	22
Unreferenced symbols defined in CSECTs . . . . .	25
Macro and copy code source summary . . . . .	25
Macro and copy code cross reference . . . . .	26
Effects of LIBMAC and PCONTROL(MCALL) options . . . . .	28
DSECT cross reference . . . . .	30
USING map . . . . .	30
General Purpose Register cross reference . . . . .	32
Diagnostic cross reference and assembler summary . . . . .	33

### Chapter 3. Controlling your assembly with options . . . . . 39

The sources of assembler options . . . . .	39
Precedence of assembler options . . . . .	39
Fixed installation default options . . . . .	40
*PROCESS OVERRIDE Statement Options . . . . .	40
ASMAOPT options . . . . .	40
Invocation options . . . . .	40
*PROCESS statement options . . . . .	41
Default options . . . . .	42
Invoking the assembler dynamically . . . . .	42
Coding rules . . . . .	42

Assembler options . . . . .	43
ADATA . . . . .	43
ALIGN . . . . .	44
ASA (z/OS and CMS) . . . . .	45
BATCH . . . . .	45
CODEPAGE . . . . .	46
COMPAT . . . . .	47
DBCS . . . . .	48
DECK . . . . .	48
DISK (CMS) . . . . .	49
DXREF . . . . .	49
ERASE (CMS) . . . . .	49
ESD . . . . .	50
EXIT . . . . .	51
FLAG . . . . .	54
FOLD . . . . .	57
GOFF (z/OS and CMS) . . . . .	57
INFO . . . . .	59
LANGUAGE . . . . .	60
LIBMAC . . . . .	60
LINECOUNT . . . . .	61
LIST . . . . .	61
MACHINE . . . . .	62
MXREF . . . . .	64
OBJECT . . . . .	65
OPTABLE . . . . .	66
PCONTROL . . . . .	67
PESTOP . . . . .	69
PRINT (CMS) . . . . .	69
PROFILE . . . . .	70
RA2 . . . . .	71
RENT . . . . .	71
RLD . . . . .	72
RXREF . . . . .	72
SECTALGN . . . . .	73
SEG (CMS) . . . . .	73
SIZE . . . . .	74
SUPRWARN . . . . .	76
SYSPARM . . . . .	76
TERM . . . . .	77
TEST . . . . .	78
THREAD . . . . .	78
TRANSLATE . . . . .	79
TYPECHECK . . . . .	79
USING . . . . .	81
WORKFILE . . . . .	83
XOBJECT (z/OS and CMS) . . . . .	84
XREF . . . . .	84

### Chapter 4. Providing user exits . . . . . 87

Exit types . . . . .	87
Specifying user exits . . . . .	88
Loading user exits . . . . .	89
Calling user exits . . . . .	90
Exit parameter list . . . . .	90

Request info pointer . . . . .	91
Buffer pointer . . . . .	98
Error buffer pointer. . . . .	98
Exit-specific information pointer . . . . .	99
DCB pointer . . . . .	99
Static assembler information pointer . . . . .	99
HLASM Services Interface pointer . . . . .	100
Error handling . . . . .	100
Exit-Specific Information Block . . . . .	100
SOURCE exit processing. . . . .	104
OPEN . . . . .	104
CLOSE . . . . .	105
READ . . . . .	105
PROCESS . . . . .	105
LIBRARY exit processing . . . . .	106
OPEN . . . . .	106
CLOSE . . . . .	107
READ . . . . .	107
PROCESS MACRO or PROCESS COPY . . . . .	108
FIND MACRO or FIND COPY . . . . .	109
END OF MEMBER . . . . .	111
LISTING exit processing. . . . .	112
OPEN . . . . .	113
CLOSE . . . . .	114
WRITE . . . . .	114
PROCESS. . . . .	115
OBJECT (z/OS and CMS) and PUNCH exit processing . . . . .	116
OPEN . . . . .	117
CLOSE . . . . .	118
WRITE . . . . .	118
PROCESS. . . . .	119
ADATA exit processing . . . . .	120
OPEN . . . . .	121
CLOSE . . . . .	121
WRITE . . . . .	122
PROCESS . . . . .	122
TERM exit processing . . . . .	123
OPEN . . . . .	124
CLOSE . . . . .	124
WRITE . . . . .	124
PROCESS . . . . .	125
Sample user exits . . . . .	126
User exit coding example . . . . .	126
OBJECT and PUNCH exit—OBJEXIT . . . . .	127
ADATA Exit—ADEXIT . . . . .	127
TERM exit—TRMEXIT . . . . .	127

## Chapter 5. Providing external functions . . . . . 145

External function processing . . . . .	145
Linkage conventions . . . . .	146
External function parameter list . . . . .	146
Request information list . . . . .	148
Pointer to user work area . . . . .	150
Pointer to static assembler information . . . . .	151
Pointer to msg buffer. . . . .	151
Pointer to return string (SETCF) . . . . .	151
Pointer to parm string <i>n</i> (SETCF). . . . .	151

## Chapter 6. Diagnosing assembly errors. . . . . 153

Assembly error diagnostic messages. . . . .	153
MNOTE statements . . . . .	155
Suppression of error messages and MNOTE statements . . . . .	156
Reference information for statements in error. . . . .	156
Abnormal assembly termination . . . . .	156
MHELP—macro trace facility . . . . .	157

## Part 2. Developing assembler programs on z/OS . . . . . 159

### Chapter 7. Assembling your program on z/OS . . . . . 161

Input to the assembler . . . . .	161
Output from the assembler. . . . .	161
Invoking the assembler on z/OS . . . . .	161
Invoking the assembler on TSO . . . . .	163
Invoking the assembler dynamically. . . . .	164
Batch assembling . . . . .	166
Input and output data sets . . . . .	166
Specifying the source data set: SYSIN . . . . .	169
Specifying the option file: ASMAOPT . . . . .	170
Specifying macro and copy code libraries: SYSLIB . . . . .	170
Specifying the listing data set: SYSPRINT . . . . .	170
Directing assembler messages to your terminal: SYSTEM . . . . .	170
Specifying object code data sets: SYSLIN and SYSPUNCH . . . . .	171
Specifying the associated data data set: SYSADATA . . . . .	171
Return codes . . . . .	171

### Chapter 8. Linking and running your program on z/OS . . . . . 173

The program management binder . . . . .	173
The loader . . . . .	174
Creating a load module . . . . .	175
Creating a load module on z/OS. . . . .	175
Creating a load module on TSO . . . . .	175
Input to the binder . . . . .	176
Data sets for binder processing . . . . .	177
Additional object modules as input . . . . .	177
Output from the binder . . . . .	178
Binder processing options . . . . .	178
Specifying binder options through JCL . . . . .	179
Specifying binder options using the TSO LINK command . . . . .	180
AMODE and RMODE attributes . . . . .	180
Overriding the defaults . . . . .	181
Detecting binder errors . . . . .	181
Running your assembled program . . . . .	181
Running your assembled program in batch . . . . .	181
Running your assembled program on TSO . . . . .	182

### Chapter 9. z/OS system services and programming considerations . . . . . 183

Adding definitions to a macro library . . . . .	183
Using cataloged procedures . . . . .	184
Cataloged procedure for assembly (ASMAC)	184
Cataloged procedure for assembly and link (ASMACL) . . . . .	185
Cataloged procedure for assembly, link, and run (ASMACLG) . . . . .	187
Cataloged procedure for assembly and run (ASMACG) . . . . .	189
Overriding statements in cataloged procedures	190
Examples of cataloged procedures . . . . .	191
Operating system programming conventions . . . . .	192
Saving and restoring general register contents	193
Ending program execution . . . . .	193
Accessing execution parameters . . . . .	194
Object program linkage . . . . .	194
Modifying program modules . . . . .	195

## **Part 3. Developing assembler programs on CMS . . . . . 197**

### **Chapter 10. Assembling your program on CMS . . . . . 199**

Input to the assembler . . . . .	199
Output from the assembler . . . . .	199
Accessing the assembler . . . . .	199
Invoking the assembler on CMS . . . . .	200
Batch assembling . . . . .	201
Controlling your assembly . . . . .	201
Input and output files . . . . .	202
Specifying the source file: SYSIN . . . . .	204
Specifying the option file: ASMAOPT . . . . .	206
Specifying macro and copy code libraries: SYSLIB . . . . .	206
Specifying the listing file: SYSPRINT . . . . .	206
Directing assembler messages to your terminal: SYSTEM . . . . .	206
Specifying object code files: SYSLIN and SYSPUNCH . . . . .	207
Specifying the associated data file: SYSADATA . . . . .	207
Return codes . . . . .	207
Diagnostic messages written by CMS . . . . .	207

### **Chapter 11. Running your program on CMS . . . . . 209**

Using the CMS LOAD and START commands . . . . .	209
Using the CMS GENMOD command . . . . .	209
Using the CMS LKED and OSRUN commands . . . . .	210
Using the CMS batch facility . . . . .	210

### **Chapter 12. CMS system services and programming considerations . . . . . 213**

Using macros . . . . .	213
Assembler macros supported by CMS . . . . .	213
Adding definitions to a macro library . . . . .	213
Operating system programming conventions . . . . .	213
Saving and restoring general register contents	213
Ending program execution . . . . .	214

Passing parameters to your assembler language program . . . . .	215
---	-----

## **Part 4. Developing assembler programs on z/VSE . . . . . 217**

### **Chapter 13. Assembling your program on z/VSE . . . . . 219**

Input to the assembler . . . . .	219
Output from the assembler . . . . .	219
Invoking the assembler in batch . . . . .	219
Invoking the assembler on ICCF . . . . .	220
Invoking the assembler dynamically . . . . .	222
Batch assembling . . . . .	223
Controlling your assembly . . . . .	224
Input and output files . . . . .	225
Specifying the source file: SYSIPT . . . . .	227
Specifying macro and copy code libraries: LIBDEF job control statement . . . . .	227
Specifying the listing file: SYSLST . . . . .	227
Directing assembler messages to your console log: SYSLOG . . . . .	227
Specifying object code files: SYSLNK and SYSPCH . . . . .	228
Specifying the associated data file: SYSADAT . . . . .	228
Return codes . . . . .	228

### **Chapter 14. Link-editing and running your program on z/VSE . . . . . 229**

The linkage editor . . . . .	229
Creating a phase . . . . .	229
Input to the linkage editor . . . . .	229
Inputting object modules . . . . .	230
Files for linkage editor processing . . . . .	230
Inputting additional object modules . . . . .	231
Linkage editor control statements . . . . .	231
Output from the linkage editor . . . . .	232
Running your assembled program . . . . .	232

### **Chapter 15. z/VSE system services and programming considerations. . . 233**

Adding definitions to a macro library . . . . .	233
Processing E-decks . . . . .	233
Operating system programming conventions . . . . .	234
Saving and restoring general register contents	234
Ending program execution . . . . .	234
Accessing execution parameters . . . . .	235

## **Part 5. Appendixes . . . . . 237**

### **Appendix A. Earlier assembler compatibility and migration . . . . . 239**

Comparison of instruction set and assembler instructions . . . . .	239
Comparison of macro and conditional assembly statements . . . . .	242
Comparison of macro and conditional assembly . . . . .	245
Comparison of language features . . . . .	248

Comparison of assembler options . . . . .	250
Comparison of assembler listing . . . . .	252
Comparison of diagnostic features . . . . .	254
Other assembler differences . . . . .	256

## **Appendix B. Cross-system portability considerations . . . . . 257**

Using machine instructions . . . . .	257
Using system macros . . . . .	257
Migrating object programs . . . . .	257

## **Appendix C. Object deck output . . . . . 259**

ESD record format . . . . .	259
TXT record format . . . . .	261
RLD record format . . . . .	261
END record format . . . . .	262
SYM record format . . . . .	263

## **Appendix D. Associated data file output . . . . . 267**

Record types . . . . .	269
Macro-only assemblies . . . . .	273
ADATA record layouts . . . . .	274
Common header section . . . . .	274
Job Identification Record—X'0000' . . . . .	276
ADATA Identification Record—X'0001' . . . . .	278
ADATA Compilation Unit Start/End Record—X'0002' . . . . .	278
Output File Information Record—X'000A' . . . . .	279
Options File Information—X'000B' . . . . .	283
Options record—X'0010' . . . . .	284
External Symbol Dictionary Record—X'0020' . . . . .	290
Source Analysis Record—X'0030' . . . . .	291
Source Error Record—X'0032' . . . . .	294
DC/DS record—X'0034' . . . . .	294
DC Extension Record—X'0035' . . . . .	301
Machine Instruction Record—X'0036' . . . . .	301
Relocation Dictionary Record—X'0040' . . . . .	301
Symbol Record—X'0042' . . . . .	302
Symbol and Literal Cross Reference Record—X'0044' . . . . .	303
Register Cross Reference Record—X'0045' . . . . .	304
Library Record—X'0060' . . . . .	305
Library Member and Macro Cross Reference Record—X'0062' . . . . .	306
User-supplied Information Record—X'0070' . . . . .	307
USING Map Record—X'0080' . . . . .	308
Statistics record—X'0090' . . . . .	309

## **Appendix E. Sample program . . . . . 313**

## **Appendix F. MHELP sample macro trace and dump . . . . . 325**

## **Appendix G. High Level Assembler messages . . . . . 335**

Message code format . . . . .	335
Message descriptions . . . . .	336
Assembly error diagnostic messages . . . . .	338

Message not known . . . . .	339
Messages . . . . .	340
Abnormal assembly termination messages . . . . .	380
ASMAHL Command Error Messages (CMS) . . . . .	385

## **Appendix H. User interface macros . . . . . 389**

## **Appendix I. Sample ADATA user exits (z/OS and CMS) . . . . . 391**

Sample ASMAXADT user exit to filter records . . . . .	391
Preparing the exit . . . . .	391
Preparing the filter modules . . . . .	392
Preparing the sample filter module ASMAXFLU . . . . .	395
Invoking the exit . . . . .	397
Sample ASMAXADC user exit to control record output . . . . .	397
Preparing the exit . . . . .	397
Invoking the exit . . . . .	397
Messages . . . . .	398
Sample ASMAXADR user exit to reformat records . . . . .	399
Preparing the exit . . . . .	399
Invoking the exit . . . . .	400
Messages . . . . .	400

## **Appendix J. Sample LISTING user exit (z/OS and CMS) . . . . . 403**

Function . . . . .	403
Preparing the exit . . . . .	403
Invoking the exit . . . . .	403
Messages . . . . .	404

## **Appendix K. Sample SOURCE user exit (z/OS and CMS) . . . . . 405**

Function . . . . .	405
Preparing the exit . . . . .	405
Invoking the exit . . . . .	405

## **Appendix L. How to generate a translation table . . . . . 407**

Preparing the translation table . . . . .	407
---	-----

## **Appendix M. How to generate a Unicode translation table . . . . . 409**

Preparing the Unicode translation table . . . . .	409
---	-----

## **Appendix N. TYPECHECK assembler option . . . . . 415**

Extensions to the DC, DS, and EQU assembler instructions . . . . .	415
Type checking behavior for REGISTER . . . . .	417
Access Register type checking . . . . .	418
General Register type checking . . . . .	419
Control Register type checking . . . . .	421
Floating-Point Register type checking . . . . .	423
Type checking behavior for MAGNITUDE . . . . .	424

## **! Appendix O. HLASM Services Interface . . . . . 427**



!	Communication and work areas . . . . .	427
!	Invoking the HLASM Services Interface . . . . .	429
!	Get storage service . . . . .	429
!	Return storage service . . . . .	430
!	Time and date service . . . . .	430
!	Write to terminal service . . . . .	430
!	Mapping the communication and work areas. . . . .	431

## **Appendix P. High Level Assembler for Linux on zSeries . . . . . 433**

Options . . . . .	433
Sources of assembler options . . . . .	433
Assembler options. . . . .	433
ELF32 option . . . . .	434
ASMAXT2E messages . . . . .	435

<b>Notices . . . . .</b>	<b>441</b>
Trademarks . . . . .	442

## **Glossary . . . . . 445**

## **Bibliography. . . . . 451**

High Level Assembler Publications . . . . .	451
Toolkit Feature Publications . . . . .	451
Related Publications (Architecture) . . . . .	451
Related Publications for z/OS . . . . .	451
Related Publications for z/VM . . . . .	451
Related Publications for z/VSE . . . . .	452

## **Index . . . . . 453**



---

## About this document

This document describes how to use the IBM High Level Assembler for z/OS & z/VM & z/VSE licensed program, hereafter referred to as High Level Assembler, or simply the assembler. It is intended to help you assemble, link, and run your High Level Assembler programs. It is meant to be used in conjunction with the *HLASM Language Reference*.

Throughout this book, we use these indicators to identify platform-specific information:

- Prefix the text with platform-specific text (for example, “Under CMS...”)
- Add parenthetical qualifications (for example, “(CMS)”)
- Marking lines above and below the text. Here are some of the marking lines we use:

<b>z/OS</b>
Informs you of information specific to z/OS®.
<b>End of z/OS</b>

<b>z/VM</b>
Informs you of information specific to z/VM®.
<b>End of z/VM</b>

<b>z/VSE</b>
Informs you of information specific to z/VSE™.
<b>End of z/VSE</b>

CMS is used in this manual to refer to Conversational Monitor System on z/VM.

---

## Who should use this document

The *HLASM Programmer's Guide* is for application programmers coding in the High Level Assembler language. To use this document, you should be familiar with the basic concepts and facilities of your operating system.

---

## Programming interface information

This document is intended to help the customer create application programs. This document documents General-Use Programming Interface and Associated Guidance Information provided by IBM High Level Assembler for z/OS & z/VM & z/VSE.

General-use programming interfaces allow the customer to write programs that obtain the services of IBM High Level Assembler for z/OS & z/VM & z/VSE.

## Organization of this document

Here is how this document is organized:

- **Part 1. Understanding and using the assembler**
  - Chapter 1, “Introduction” describes High Level Assembler, and defines the environmental requirements for using the assembler.
  - Chapter 2, “Using the assembler listing” describes the content and format of the assembler listing.
  - Chapter 3, “Controlling your assembly with options” describes the assembler options that you can use to control the assembly of your program.
  - Chapter 4, “Providing user exits” describes how you can provide user exits to compliment the assembler’s data-set processing.
  - Chapter 5, “Providing external functions” describes how to provide user-supplied routines in conditional assembly instructions to set the value of SET symbols.
  - Chapter 6, “Diagnosing assembly errors” describes the purpose and format of error messages, MNOTEs, and the MHELP trace facility.
- **Part 2. Developing Assembler Programs on z/OS**
  - Chapter 7, “Assembling your program on z/OS” describes the different methods of assembling your program on z/OS, including invoking the assembler with job control statements, invoking the assembler on TSO/E, invoking the assembler dynamically, and batch assembling.
  - Chapter 8, “Linking and running your program on z/OS” describes linking, creating load modules, input and output for the linkage editor and binder, detecting linking errors, and running your program on z/OS.
  - Chapter 9, “z/OS system services and programming considerations” describes the z/OS system services that you can use to maintain macro definitions in a macro library, and the cataloged procedures that are provided to help you assemble, link-edit, and run your program on z/OS. This chapter also discusses programming topics such as standard entry and exit procedures.
- **Part 3. Developing Assembler Programs on CMS**
  - Chapter 10, “Assembling your program on CMS” describes how to invoke the assembler on CMS.
  - Chapter 11, “Running your program on CMS” describes how to load and run your program on CMS.
  - Chapter 12, “CMS system services and programming considerations” describes the CMS system services that you can use to maintain members in a macro library. It also discusses programming topics such as standard entry and exit procedures.
- **Part 4. Developing Assembler Programs on z/VSE**
  - Chapter 13, “Assembling your program on z/VSE” describes how to invoke the assembler on z/VSE.
  - Chapter 14, “Link-editing and running your program on z/VSE” describes link-editing, creating load modules, input and output for the linkage editor, detecting link-edit errors, and running your program on z/VSE.
  - Chapter 15, “z/VSE system services and programming considerations” describes the VSE system services that you can use to maintain macro definitions in a macro library, and the cataloged procedures that are provided to help you assemble, link-edit, and run your program on VSE. This chapter also discusses programming topics such as standard entry and exit procedures.

- **Appendixes**

- Appendix A, “Earlier assembler compatibility and migration” provides a comparison of High Level Assembler and Assembler H Version 2, and High Level Assembler and the DOS/VSE Assembler.
  - Appendix B, “Cross-system portability considerations” contains information that helps you prepare your program for running under a different operating system.
  - Appendix C, “Object deck output” describes the format of the object module generated by the assembler.
  - Appendix D, “Associated data file output” describes the format of the associated data file records generated by the assembler.
  - Appendix E, “Sample program” provides a sample program that demonstrates many of the assembler language features.
  - Appendix F, “MHELP sample macro trace and dump” provides a sample program listing which shows the primary functions of MHELP.
  - Appendix G, “High Level Assembler messages” describes the error diagnostic messages, abnormal termination messages, and CMS command error messages issued by the assembler.
  - Appendix H, “User interface macros” lists the macros that are provided as Programming Interfaces with High Level Assembler.
  - Appendix I, “Sample ADATA user exits (z/OS and CMS)” provides a description of the sample ADATA user exits supplied with High Level Assembler.
  - Appendix J, “Sample LISTING user exit (z/OS and CMS)” provides a description of the sample LISTING user exit supplied with High Level Assembler.
  - Appendix K, “Sample SOURCE user exit (z/OS and CMS)” provides a description of the sample SOURCE user exit supplied with High Level Assembler to read variable length input files.
  - Appendix L, “How to generate a translation table” provides instructions for generating a translation table to convert the characters contained in character data constants and literals.
  - Appendix N, “TYPECHECK assembler option” provides information about how the TYPECHECK option controls the type checking of machine instruction operands performed by the assembler.
  - Appendix O, “HLASM Services Interface” describes the cooperative interface between High Level Assembler and its I/O exits.
  - Appendix P, “High Level Assembler for Linux on zSeries” provides information relevant to the Linux™ on zSeries® implementation of High Level Assembler.
- The Glossary defines the terms used in this document.
  - The Bibliography lists the IBM Publications referred to within this document.

---

## IBM High Level Assembler for z/OS & z/VM & z/VSE Publications

High Level Assembler runs on z/OS, z/VM and z/VSE. These publications are described in this section.

### Hardcopy Publications

The books in the High Level Assembler library are shown in Table 1 on page xii. This figure shows which books can help you with specific tasks, such as

application programming.

*Table 1. IBM High Level Assembler for z/OS & z/VM & z/VSE Publications*

Task	Publication	Order Number
Evaluation and Planning	HLASM V1R6 General Information	GC26-4943
Installation and Customization	HLASM V1R6 Installation and Customization Guide	SC26-3494
	HLASM V1R6 Programmer's Guide	SC26-4941
	HLASM V1R6 Toolkit Feature Installation Guide	GC26-8711
Application Programming	HLASM V1R6 Programmer's Guide	SC26-4941
	HLASM V1R6 Language Reference	SC26-4940
	HLASM V1R6 General Information	GC26-4943
	HLASM V1R6 Toolkit Feature User's Guide	GC26-8710
	HLASM V1R6 Toolkit Feature Interactive Debug Facility User's Guide	GC26-8709
Diagnosis	HLASM V1R6 Installation and Customization Guide	SC26-3494
Warranty	HLASM V1R6 Licensed Program Specifications	GC26-4944

### *HLASM General Information*

Introduces you to the High Level Assembler product by describing what it does and which of your data processing needs it can fill. It is designed to help you evaluate High Level Assembler for your data processing operation and to plan for its use.

### *HLASM Installation and Customization Guide*

Contains the information you need to install and customize, and diagnose failures in, the High Level Assembler product.

The diagnosis section of the book helps users determine if a correction for a similar failure has been documented previously. For problems not documented previously, the book helps users to prepare an APAR. This section is for users who suspect that High Level Assembler is not working correctly because of some defect.

### *HLASM Language Reference*

Presents the rules for writing assembler language source programs to be assembled using High Level Assembler.

### *HLASM Licensed Program Specifications*

Contains a product description and product warranty information for High Level Assembler.

### *HLASM Programmer's Guide*

Describes how to assemble, debug, and run High Level Assembler programs.

### *HLASM Toolkit Feature Installation and Customization Guide*

Contains the information you need to install and customize, and diagnose failures in, the High Level Assembler Toolkit Feature.

### *HLASM Toolkit Feature User's Guide*

Describes how to use the High Level Assembler Toolkit Feature.

### *HLASM Toolkit Feature Debug Reference Summary*

Contains a reference summary of the High Level Assembler Interactive Debug Facility.

### *HLASM Toolkit Feature Interactive Debug Facility User's Guide*

Describes how to use the High Level Assembler Interactive Debug Facility.

## Online publications

The High Level Assembler publications are available in the following softcopy formats:

- *z/OS Collection* CD-ROM: SK3T-4269 (Book), SK3T-8334 (PDF)
- *z/VM Collection* CD-ROM: SK2T-2401 (Book), SK3T-8330 (PDF)
- *z/VSE Collection* CD-ROM: SK2T-2402 (Book), SK3T-8331 (PDF)

For more information about High Level Assembler, see the High Level Assembler web site, at

<http://www-306.ibm.com/software/awdtools/hlasm/>

---

## Related publications

See “Bibliography” on page 451 for a list of publications that supply information you might need while using High Level Assembler.

---

## Syntax notation

Throughout this book, syntax descriptions use the structure defined below.

- Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

The ►— symbol indicates the beginning of a statement.

The —→ symbol indicates that the statement syntax is continued on the next line.

The ►— symbol indicates that a statement is continued from the previous line.

The —► indicates the end of a statement.


Diagrams of syntactical units other than complete statements start with the ►— symbol and end with the —→ symbol.

- **Keywords** appear in uppercase letters (for example, ASPACE) or upper and lower case (for example, PATHFile). They must be spelled exactly as shown. Lower case letters are optional (for example, you could enter the PATHFile keyword as PATHF, PATHFI, PATHFIL or PATHFILE).


**Variables** appear in all lowercase letters in a special typeface (for example, *integer*). They represent user-supplied names or values.

- If punctuation marks, parentheses, or such symbols are shown, they must be entered as part of the syntax.
- Required items appear on the horizontal line (the main path).


## Syntax notation




- Optional items appear below the main path. If the item is optional and is the default, the item appears above the main path.




- When you can choose from two or more items, they appear vertically in a stack. If you **must** choose one of the items, one item of the stack appears on the main path.



If choosing one of the items is optional, the whole stack appears below the main path.




- An arrow returning to the left above the main line indicates an item that can be repeated. When the repeat arrow contains a separator character, such as a comma, you must separate items with the separator character.



A repeat arrow above a stack indicates that you can make more than one choice from the stacked items, or repeat a single choice.

The following example shows how the syntax is used.





- A** The item is optional, and can be coded or not.
- B** The INSTRUCTION key word must be specified and coded as shown.
- C** The item referred to by “fragment” is a required operand. Allowable choices for this operand are given in the fragment of the syntax diagram shown below “fragment” at the bottom of the diagram. The operand can also be repeated. That is, more than one choice can be specified, with each choice separated by a comma.

## Syntax notation

---

## Summary of changes

<b>Date of Publication</b>	July 2008
<b>Form of Publication</b>	Sixth Edition, SC26-4941-04

### **New features**

- High Level Assembler for Linux on System z<sup>™</sup>

### **New options**

- WORKFILE

### **Changed assembler instructions**

- DC/DS
  - Decimal floating-point constants
  - Unsigned binary constants
  - Tags allowing use of macros and machine or assembler instructions with identical mnemonics.

### **Changed assembler statements**

- Parts with text
- OPTABLE option for ACONTROL

### **Services Interface**

- HLASM Services Interface for I/O exits added

### **Miscellany**

- Qualifiers identified in symbol cross-reference.

## Summary of changes

---

## Part 1. Understanding and using the assembler

<b>Chapter 1. Introduction</b> . . . . .	3	LIBMAC	60
Requirements . . . . .	3	LINECOUNT.	61
System requirements. . . . .	3	LIST. . . . .	61
Machine requirements . . . . .	3	MACHINE . . . . .	62
Storage requirements . . . . .	4	MXREF. . . . .	64
Compatibility . . . . .	4	OBJECT . . . . .	65
Assembler language support . . . . .	4	OPTABLE . . . . .	66
Migration considerations . . . . .	5	PCONTROL . . . . .	67
 		PESTOP . . . . .	69
<b>Chapter 2. Using the assembler listing</b> . . . . .	7	PRINT (CMS). . . . .	69
High Level Assembler option summary . . . . .	8	PROFILE . . . . .	70
External Symbol Dictionary (ESD) . . . . .	11	RA2 . . . . .	71
Source and object . . . . .	14	RENT . . . . .	71
Relocation dictionary (RLD) . . . . .	21	RLD . . . . .	72
Ordinary symbol and literal cross reference. . . . .	22	RXREF . . . . .	72
Unreferenced symbols defined in CSECTs . . . . .	25	SECTALGN . . . . .	73
Macro and copy code source summary . . . . .	25	SEG (CMS) . . . . .	73
Macro and copy code cross reference . . . . .	26	SIZE. . . . .	74
Effects of LIBMAC and PCONTROL(MCALL)		SUPRWARN . . . . .	76
options . . . . .	28	SYSARM . . . . .	76
DSECT cross reference. . . . .	30	TERM . . . . .	77
USING map . . . . .	30	TEST . . . . .	78
General Purpose Register cross reference . . . . .	32	THREAD . . . . .	78
Diagnostic cross reference and assembler summary	33	TRANSLATE . . . . .	79
 		TYPECHECK. . . . .	79
<b>Chapter 3. Controlling your assembly with options</b> . . . . .	39	USING . . . . .	81
The sources of assembler options . . . . .	39	WORKFILE . . . . .	83
Precedence of assembler options . . . . .	39	XOBJECT (z/OS and CMS) . . . . .	84
Fixed installation default options . . . . .	40	XREF . . . . .	84
*PROCESS OVERRIDE Statement Options . . . . .	40	 	
ASMAOPT options . . . . .	40	<b>Chapter 4. Providing user exits</b> . . . . .	87
Invocation options . . . . .	40	Exit types . . . . .	87
*PROCESS statement options . . . . .	41	Specifying user exits . . . . .	88
Default options . . . . .	42	Loading user exits . . . . .	89
Invoking the assembler dynamically . . . . .	42	Calling user exits . . . . .	90
Coding rules . . . . .	42	Exit parameter list . . . . .	90
Assembler options . . . . .	43	Request info pointer . . . . .	91
ADATA. . . . .	43	Parameter list version . . . . .	91
ALIGN . . . . .	44	Exit type . . . . .	92
ASA (z/OS and CMS) . . . . .	45	Request type . . . . .	92
BATCH. . . . .	45	Options. . . . .	92
CODEPAGE . . . . .	46	EXITCTLn . . . . .	94
COMPAT . . . . .	47	Return code . . . . .	94
DBCS . . . . .	48	Reason code . . . . .	95
DECK . . . . .	48	Buffer length . . . . .	96
DISK (CMS) . . . . .	49	Error buffer length . . . . .	97
DXREF . . . . .	49	Error severity. . . . .	97
ERASE (CMS) . . . . .	49	User-defined field . . . . .	98
ESD . . . . .	50	Common user field. . . . .	98
EXIT. . . . .	51	Buffer pointer . . . . .	98
FLAG . . . . .	54	Error buffer pointer. . . . .	98
FOLD . . . . .	57	Exit-specific information pointer . . . . .	99
GOFF (z/OS and CMS) . . . . .	57	DCB pointer . . . . .	99
INFO . . . . .	59	Static assembler information pointer . . . . .	99
LANGUAGE . . . . .	60	HLASM VRM . . . . .	99
		PTF level. . . . .	100

System ID . . . . .	100
Numeric version . . . . .	100
I HLASM Services Interface pointer . . . . .	100
Error handling . . . . .	100
Exit-Specific Information Block . . . . .	100
SOURCE exit processing. . . . .	104
OPEN . . . . .	104
CLOSE . . . . .	105
READ . . . . .	105
PROCESS . . . . .	105
LIBRARY exit processing . . . . .	106
OPEN . . . . .	106
CLOSE . . . . .	107
READ . . . . .	107
PROCESS MACRO or PROCESS COPY . . . . .	108
FIND MACRO or FIND COPY . . . . .	109
System variables . . . . .	109
Nesting COPY instructions and macro definitions . . . . .	110
END OF MEMBER . . . . .	111
LISTING exit processing. . . . .	112
OPEN . . . . .	113
CLOSE . . . . .	114
WRITE . . . . .	114
PROCESS. . . . .	115
OBJECT (z/OS and CMS) and PUNCH exit processing . . . . .	116
OPEN . . . . .	117
CLOSE . . . . .	118
WRITE . . . . .	118
PROCESS. . . . .	119
ADATA exit processing . . . . .	120
OPEN . . . . .	121
CLOSE . . . . .	121
WRITE . . . . .	122
PROCESS . . . . .	122
TERM exit processing . . . . .	123
OPEN . . . . .	124
CLOSE . . . . .	124
WRITE . . . . .	124
PROCESS . . . . .	125
Sample user exits . . . . .	126
User exit coding example . . . . .	126
OBJECT and PUNCH exit—OBJEXIT . . . . .	127
ADATA Exit—ADEXIT . . . . .	127
TERM exit—TRMEXIT . . . . .	127

## Chapter 5. Providing external functions. . . . . 145

External function processing . . . . .	145
Linkage conventions . . . . .	146
External function parameter list . . . . .	146
Request information list . . . . .	148
Parameter list version . . . . .	149
Function type . . . . .	149
Number of parameters . . . . .	149
Return code . . . . .	149
Flag byte . . . . .	149
Reserved . . . . .	149
Msg length . . . . .	150
Msg severity . . . . .	150
Return value (SETAF) . . . . .	150

Parm value <i>n</i> (SETAF) . . . . .	150
Return string length (SETCF) . . . . .	150
Parm string <i>n</i> length (SETCF) . . . . .	150
Pointer to user work area . . . . .	150
Pointer to static assembler information . . . . .	151
Pointer to msg buffer. . . . .	151
Pointer to return string (SETCF) . . . . .	151
Pointer to parm string <i>n</i> (SETCF). . . . .	151

## Chapter 6. Diagnosing assembly errors. . . . . 153

Assembly error diagnostic messages. . . . .	153
MNOTE statements . . . . .	155
Suppression of error messages and MNOTE statements . . . . .	156
Reference information for statements in error. . . . .	156
Abnormal assembly termination . . . . .	156
MHELP—macro trace facility . . . . .	157

---

## Chapter 1. Introduction

IBM High Level Assembler for z/OS & z/VM & z/VSE is an IBM licensed program that can be used to assemble assembler language programs that use the following machine instructions:

- System/370™
- System/370 Extended Architecture (370-XA)
- Enterprise Systems Architecture/370™ (ESA/370)
- Enterprise Systems Architecture/390 (ESA/390)
- z/Architecture™

---

## Requirements

This section describes the operating systems, the processors, and the amount of storage required to run High Level Assembler.

### System requirements

High Level Assembler runs under the operating systems listed below. Unless otherwise stated, the assembler also operates under subsequent versions, releases, and modification levels of these systems:

- OS/390® Version 2 Release 10.0 (5647-A01)
- VM/ESA® Version 3 Release 1.0 (5654-A17)
- z/VM Version 5 Release 2 (5741-A05)
- VSE/ESA™ Version 2 Release 6 (5690-VSE)
- z/VSE Version 3 Release 1 and Version 4 (5686-CF8)
- z/OS Version 1 Release 2.0 (5694-A01)

High Level Assembler supports the operation codes available with the following mode processors:

- Extended Architecture (370-XA)
- Enterprise Systems Architecture/370 (ESA/370)
- Enterprise Systems Architecture/390 (ESA/390)
- z/Architecture

### Machine requirements

*For assembling High Level Assembler programs:* Programs written using High Level Assembler can be assembled, including use of the z/Architecture processor machine instructions, the Extended Architecture mode processor machine instructions, and Enterprise System Architecture mode processor machine instructions, on all System/370 family and its follow-on machines supporting the following operating systems:

- z/OS
- z/VM
- z/VSE
- OS/390
- VM/ESA
- VSE/ESA

You might require an operating system-specific macro library to assemble programs that run under that operating system, depending on macro usage.

## Requirements

**For running High Level Assembler programs:** A generated object program using z/Architecture, Extended Architecture (370-XA), Enterprise Systems Architecture/370 (ESA/370), Enterprise Systems Architecture/390 (ESA/390), Enterprise Systems/9000 (ES/9000<sup>®</sup>) or Vector instructions can be run only on an applicable processor under an operating system that provides the necessary architecture support for the instructions used.

**Tape device:** High Level Assembler is distributed on one of the following:

- Standard labeled 9-track magnetic tape written at 6250 bpi
- 3480 tape cartridge

An appropriate tape device is required for installation.

**Double-byte data:** Double-byte data can be displayed, entered, or both, in their national language representation on the following:

- IBM 3800-8 system printer
- IBM 3200 system printer
- IBM 3820 remote printer
- IBM PS/55 family as an IBM 3270 terminal

## Storage requirements

**Virtual storage:** High Level Assembler requires a minimum of 610K bytes of main storage. 410K bytes of storage are required for High Level Assembler load modules. The rest of the storage allocated to the assembler is used for assembler working storage.

**Auxiliary storage space:** Depending on the assembler options used, auxiliary storage space might be required for the following data sets:

- System input
- Macro instruction library—either system or private or both
- Print output
- Object module output
- Associated data output

**Library space:** The space requirements for the High Level Assembler load modules (or phases) and procedures are provided in the *HLASM Installation and Customization Guide*.

**Installation:** Please refer to *HLASM Installation and Customization Guide* for installation requirements.

---

## Compatibility

This section describes source program compatibility and migration issues that you need to consider before using High Level Assembler.

## Assembler language support

The assembler language supported by High Level Assembler has functional extensions to the languages supported by Assembler H Version 2 and the DOS/VSE Assembler. High Level Assembler uses the same language syntax, function, operation, and structure as these earlier assemblers. The functions provided by the Assembler H Version 2 macro facility are all provided by High Level Assembler.



## Migration considerations

*Source Programs:* Migration from High Level Assembler Release 1, High Level Assembler Release 2, High Level Assembler Release 3, High Level Assembler Release 4, High Level Assembler Release 5, Assembler H Version 2 or DOS/VSE Assembler to High Level Assembler Release 6, requires an analysis of existing assembler language programs to ensure that they do not contain macro instructions with names that conflict with the High Level Assembler Release 6 symbolic operation codes, or SET symbols with names that conflict with the names of High Level Assembler Release 6 system variable symbols.

With the exception of these possible conflicts, and with appropriate High Level Assembler option values, assembler language source programs written for High Level Assembler Release 1, High Level Assembler Release 2, High Level Assembler Release 3, High Level Assembler Release 4, High Level Assembler Release 5, Assembler H Version 2 or the DOS/VSE Assembler, that assemble without warning or error diagnostic messages, should assemble correctly using High Level Assembler Release 6.

*Object Programs:* Object programs generated by High Level Assembler Release 6 in any one of the supported operating systems can be migrated to any other of the supported operating systems for execution.

The object programs being migrated must be link-edited in the target operating system environment before execution.

You should be aware of the differences in the code generated by system macros in the supported operating systems. Operational facilities available on the source operating system but not available on the target operating system should not be specified for any program which is required to be compatible, either during assembly or link-edit.



---

## Chapter 2. Using the assembler listing

This chapter tells you how to interpret the printed listing produced by the assembler. The listing is obtained only if the option LIST is in effect. Parts of the listing can be suppressed by using other options; for information on the listing options, refer to Chapter 3, “Controlling your assembly with options,” on page 39.

The High Level Assembler listing consists of up to twelve sections, ordered as follows:

- High Level Assembler Option Summary
- External Symbol Dictionary (ESD)
- Source and Object
- Relocation Dictionary (RLD)
- Ordinary Symbol and Literal Cross Reference
- Unreferenced Symbols Defined in CSECTs
- Macro and Copy Code Source Summary
- Macro and Copy Code Cross Reference
- DSECT Cross Reference
- USING Map
- General Purpose Register Cross Reference
- Diagnostic Cross Reference and Assembler Summary

The following assembler options are used to control the format, and which sections to produce, of the assembler listing:

**ASA** (z/OS and CMS) Allows you to use American National Standard printer control characters, instead of machine printer control characters.

**DXREF** Produces the DSECT Cross Reference section.

**ESD** Produces the External Symbol Dictionary section.

**EXIT(PRTEXTIT(mod3))** Allows you to supply a listing exit to replace or complement the assembler’s listing output processing.

**LANGUAGE** Produces error diagnostic messages in the following languages:

- English mixed case (EN)
- English uppercase (UE)
- German (DE)
- Japanese (JP)
- Spanish (ES)

When you select either of the English languages, the assembler listing headings are produced in the same case as the diagnostic messages.

When you select either the German language or the Spanish language, the assembler listing headings are produced in mixed case English.

When you select the Japanese language, the assembler listing headings are produced in uppercase English.

The assembler uses the installation default language for messages produced in CMS by the ASMAHL command.

## Using the assembler listing

<b>LINECOUNT</b>	Allows you to specify how many lines should be printed on each page.
<b>LIST</b>	Controls the format of the Source and Object section of the listing. NOLIST suppresses the entire listing.
<b>MXREF</b>	Produces one, or both, of the Macro and Copy Code Source Summary and Macro and Copy Code Cross Reference sections.
<b>PCONTROL</b>	Controls which statements are printed in the listing, and overrides some PRINT instructions.
<b>RLD</b>	Produces the Relocation Dictionary section.
<b>RXREF</b>	Produces the General Purpose Register Cross Reference section.
<b>USING(MAP)</b>	Produces the Using Map section.
<b>XREF</b>	Produces one, or both, of the Ordinary Symbol and Literal Cross Reference and the Unreferenced Symbols Defined in CSECTs sections.

The following additional options can be specified when you run the assembler on CMS:

<b>LINECOUN</b>	An abbreviation of the LINECOUNT option.
<b>PRINT</b>	The assembler listing is written to the virtual printer instead of to a disk file.

The sections in the listing are described on the following pages.

---

## High Level Assembler option summary

High Level Assembler provides a summary of the options current for the assembly, including:

- A list of the overriding parameters specified in the ASMAOPT file (z/OS and CMS) or library member ASMAOPT.USER (z/VSE).
- A list of the overriding parameters specified when the assembler was called
- The options specified on \*PROCESS statements
- In-line error diagnostic messages for any overriding parameters and \*PROCESS statements in error

You cannot suppress the option summary unless you suppress the entire listing, or you supply a user exit to control which lines are printed.

On z/OS and CMS, High Level Assembler provides a sample LISTING exit that allows you to suppress the option summary or print it at the end of the listing. See Appendix J, “Sample LISTING user exit (z/OS and CMS),” on page 403.

Figure 1 shows an example of the High Level Assembler Option Summary. The example includes assembler options that have been specified in the following option sources:

- ASMAOPT file
- Invocation parameters
- PROCESS statements including an example specifying the OVERRIDE keyword.

The example shows a number of error diagnostic messages relating to the conflicts and errors in the options specified.

High Level Assembler Option Summary		Page	1
		<b>1</b>	<b>2</b>
		HLASM R6.0	2008/07/11 17.48
0	Overriding ASMAOPT Parameters - sysparm(thisisatestsysparm),rxref		
	Overriding Parameters- NOOBJECT,language(en),size(4meg),xref(short,unrefs),nomxref,norxref,adata,noadata		
	Process Statements- OVERRIDE(ADATA,MXREF(full))		
	ALIGN		
	noDBCS		
	MXREF(FULL),nolibmac		
	FLAG(0)		
	noFOLD,LANGUAGE(ue)		
	NORA2		
	NODBCS		
	XREF(FULL)		
	<b>3</b>		
	** ASMA400W Error in invocation parameter - size(4meg)		
	** ASMA438N Attempt to override ASMAOPT parameter. Option norxref ignored.		
	** ASMA425N Option conflict in invocation parameters. noadata overrides an earlier setting.		
	** ASMA423N Option ADATA, in a *PROCESS OVERRIDE statement conflicts with invocation or default option. Option is not permitted in a *PROCESS statement and has been ignored.		
	** ASMA422N Option LANGUAGE(ue) is not valid in a *PROCESS statement.		
	** ASMA437N Attempt to override invocation parameter in a *PROCESS statement. Suboption FULL of XREF option ignored.		
	Options for this Assembly		
	<b>4</b>		
3	NOADATA		
5	ALIGN		
	NORASA		
	BATCH		
	CODEPAGE(047C)		
	NOCOMPAT		
5	NODBCS		
	NODECK		
	DXREF		
	ESD		
	NOEXIT		
5	FLAG(0,ALIGN,CONT,EXLITW,NOIMPLEN,NOPAGE0,PUSH,RECORD,NOSUBSTR,USING0)		
5	NOFOLD		
	NOGOFF		
	NOINFO		
3	LANGUAGE(EN)		
5	NOLIBMAC		
	LINECOUNT(60)		
	LIST(121)		
	MACHINE(,NOLIST)		
1	MXREF(FULL)		
3	NOOBJECT		
	OPTABLE(UNI,NOLIST)		
	NOPCONTROL		
	NOPESTOP		
	NOPROFILE		
5	NORA2		
	NORENT		
	RLD		
2	RXREF		
	SECTALGN(8)		
	SIZE(MAX)		
	NOSUPRWARN		
2	SYSARM(thisisatestsysparm)		
	NOTERM		

Figure 1. Option summary including options specified on \*PROCESS statements (Part 1 of 2)

## High Level Assembler option summary

1	High Level Assembler Option Summary				Page	2
-					HLASM R6.0	2008/07/11 17.48
0	NOTEST					
	THREAD					
	NOTRANSlate					
	TYPECHECK(MAGNITUDE,REGISTER)					
	USING(NOLIMIT,MAP,WARN(15))					
3	XREF(SHORT,UNREFS)					
	NOWORKFILE					
5	No Overriding DD Names					
1	External Symbol Dictionary				Page	3
-Symbol	Type	Id	Address	Length	Owner	Id
0A	SD	00000001	00000000	00000000	00	00
1	Active Usings: None				Page	4
0	Loc	Object Code	Addr1	Addr2	Stmt	Source Statement
0					6	1 *PROCESS OVERRIDE(ADATA,MXREF(full))
					2	*PROCESS ALIGN
					3	*PROCESS noDBCS
					4	*PROCESS MXREF(FULL),no libmac
					5	*PROCESS FLAG(0)
					6	*PROCESS noFOLD,LANGUAGE(ue)
					7	*PROCESS NORA2
					8	*PROCESS NODBCS
					9	*PROCESS XREF(FULL)
000000			00000	00000	10	A CSECT
	R:F	00000			11	USING *,15

Figure 1. Option summary including options specified on \*PROCESS statements (Part 2 of 2)

The highlighted numbers in the example are:

- 1 The product description. Shown on each page of the assembler listing. (You can use the TITLE instruction to generate individual headings for each page of the source and object program listing.)
- 2 The date and the time of the assembly.
- 3 Error diagnostic messages for overriding parameters and \*PROCESS statements. These immediately follow the list of \*PROCESS statement options. The error diagnostic messages are:

#### ASMA400W -

The value specified as the size option is not valid. The valid option is SIZE(4M).

#### ASMA438N -

The option RXREF is specified in the ASMAOPT file and the conflicting option NORXREF is specified as an invocation parameter. The ASMAOPT options have precedence over the invocation parameters and the NORXREF option is ignored.

#### ASMA425N -

The ADATA option specified as an invocation parameter overrides the option NOADATA which was also specified as an invocation parameter. When conflicting options are received from the same source, the last occurrence takes precedence.

#### ASMA423N -

The option ADATA has been specified in a \*PROCESS statement with the OVERRIDE option. The option cannot be set by a \*PROCESS statement, and the option conflicts with an invocation or default option. This message is printed when an option that cannot be set by a \*PROCESS statement (See “\*PROCESS statement

options” on page 41) is included in a \*PROCESS OVERRIDE statement and the option conflicts with an invocation or default option. If the option does not conflict with the invocation or default option no message is printed.

### ASMA422N -

The option LANGUAGE is not permitted in a \*PROCESS statement.

### ASMA437N -

The option XREF(FULL) which is specified in the last \*PROCESS statement conflicts with the option NORXREF which is specified as an invocation parameter. The option XREF(FULL) is ignored.

- 4** A flag beside each option indicates the source of the option. This table shows the sources:

*Table 2. Flags used in the option summary*

Flag	Meaning
1	The option came from a *PROCESS OVERRIDE statement.
2	The option came from the ASMAOPT options file (z/OS and CMS) or ASMAOPT.USER library member (z/VSE).
3	The option came from the invocation parameters.
4	The permanent job control options set by the z/VSE command STDOPT.
5	The option came from a *PROCESS statement.
(space)	The option came from the installation defaults.

- 5** On z/OS and CMS, if the assembler has been called by a program and any standard (default) ddnames have been overridden, both the default ddnames and the overriding ddnames are listed. Otherwise, this statement appears:

No Overriding DD Names

- 6** The \*PROCESS statements are written as comment statements in the Source and Object section of the listing.

See “Precedence of assembler options” on page 39.

## External Symbol Dictionary (ESD)

This section of the listing contains the external symbol dictionary information passed to the linkage editor or loader, or z/OS Program Management Binder, in the object module.

This section helps you find references between modules in a multimodule program. The ESD may be particularly helpful in debugging the running of large programs constructed from several modules.

The ESD entries describe the control sections, external references, classes, parts and entry points in the assembled program. There are nine types of ESD entries (SD, ED, LD, ER, PC, PR, CM, XD, and WX). Table 3 on page 12 shows the ESD entries when you specify the NOGOFF option. Table 4 on page 12 shows the ESD entries when you specify the GOFF option. For each of the different types of ESD entries, an X indicates which of the fields have values.

## External Symbol Dictionary

Table 3. Types of ESD entries when NOGOFF option specified

SYMBOL	TYPE	ID	ADDR	LENGTH	Owner ID	FLAGS
X	SD	X	X	X		X
X	LD		X		X	
X	ER	X				
	PC	X	X	X		X
X	CM	X	X	X		X
X	XD	X	X	X		
X	WX	X				

Table 4. Types of ESD entries when GOFF option specified

SYMBOL	TYPE	ID	ADDR	LENGTH	Owner ID	FLAGS
X	SD	X				X <sup>1</sup>
X	ED	X	X	X	X	X
X	LD	X	X		X	X
X	PR	X	X	X	X	X
X	ER	X			X	
X	CM	X	X		X	X
X	XD	X	X	X		
X	WX	X			X	

**Note:**

1. Only if the SD ESDID entry is associated with CM ESDID entry.

Figure 2 is an example of the *External Symbol Dictionary* generated with the GOFF assembler option, and is followed by a description of its contents.

**Note:** This sample is intended to show the various fields and possible values and is not meant to be an actual listing.

External Symbol Dictionary								Page	2
1	2	3	4	5	6	7	8		
Symbol	Type	Id	Address	Length	Owner Id	Flags	Alias-of		
SAMP01	SD	00000001			00000001				
B_PRV	ED	00000002			00000001	00			
B_TEXT	ED	00000003	00000000	000000E0	00000001	00			
SAMP01	LD	00000004	00000000		00000003	00			
ENTRY1	LD	00000005	00000000		00000003	00			
KL_INST	SD	00000006							
B_PRV	ED	00000007			00000006				
B_TEXT	ED	00000008	00000000	00000000	00000006	00			
KL_INST	CM	00000009	00000000		00000008	00			
	SD	0000000A							
B_PRV	ED	0000000B			0000000A				
B_TEXT	ED	0000000C	000000E0	00000000	0000000A	00			
Date0001	ER	0000000D			0000000A		RCNVDATE		
RCNVTIME	ER	0000000E			0000000A				

Figure 2. External Symbol Dictionary listing

- 1 The name of every external dummy section, control section, entry point, external symbol, part, and class. If the external dummy section, control section, entry point, part or external symbol has a corresponding ALIAS instruction, the symbol shows the operand of the ALIAS instruction.



When you specify the GOFF assembler option on z/OS or CMS, the assembler generates two ED entries, the first with a symbol name of B\_PRV and the second with a symbol name of B\_TEXT.

**2** The type designator for the entry, as shown in the table:

<b>SD</b>	Control section definition. The symbol appeared in the name field of a START, CSECT, or RSECT instruction.  When you specify the GOFF assembler option, on z/OS or CMS, the assembler will generate an SD entry type for the symbol which appears in the field name of a COM instruction.
<b>LD</b>	Label definition. The symbol appeared as the operand of an ENTRY statement.  When you specify the GOFF assembler option, on z/OS or CMS, the assembler generates an entry type of LD for each CSECT and RSECT name.
<b>ER</b>	External reference. The symbol appeared as the operand of an EXTRN statement, or appeared as an operand of a V-type address constant.
<b>PC</b>	Unnamed control section definition (private code). A CSECT, RSECT, or START statement that commences a control section that does not have a symbol in the name field, or a control section that is commenced (by any instruction which affects the location counter) before a CSECT, RSECT, or START.  When you specify the GOFF assembler option, on z/OS or CMS, the assembler does not generate an LD entry for a private code section. For private code, the assembler creates an SD entry type with a blank name.
<b>PR</b>	Part definition. The symbol appeared in the PART parameter of a CATTR statement.
<b>CM</b>	Common control section definition. The symbol appeared in the name field of a COM statement.
<b>XD</b>	External dummy section. The symbol appeared in the name field of a DXD statement or the operand of a Q-type address constant.  The external dummy section is also called a pseudo register in the applicable <i>Linkage Editor and Loader</i> document, and z/OS DFSMS <i>Program Management</i> .
	<b>Note:</b> The alignment value of an external dummy section is displayed in the address field of the External Symbol Dictionary. However, its value is encoded in different fields of the object file, not the address.
<b>WX</b>	Weak external reference. The symbol appeared as an operand in a WXTRN statement.
<b>ED</b>	Element definition (one for each class). The symbol appeared as an operand in a CATTR statement.  When you specify the NOGOFF assembler option, on z/OS or CMS, the assembler does not generate an entry type of ED.  For further information, refer to z/OS DFSMS <i>Program Management</i> .

## External Symbol Dictionary

- 3** The external symbol dictionary identification number (ESDID). The number is a unique 8-digit hexadecimal number identifying the entry.
- 4** The address of the symbol (in hexadecimal notation) for SD- and LD-type entries, and spaces for ER- and WX-type entries. For PC- PR- and CM-type entries, it indicates the beginning address of the control section. For XD-type entries, it indicates the alignment with a number one less than the number of bytes in the unit of alignment. For example, 7 indicates doubleword alignment.
- 5** The assembled length, in bytes, of the section, element, or DXD (in hexadecimal notation).
- 6** The ESDID of the control section in which the LD ID is the ESDID of the following, depending on the type:
- LD** The control section in which the label is defined.
  - ED** The control section to which this element belongs.
  - CM** The control section in which the common control section is defined.
  - ER** The control section in which the external reference was declared.
  - PR** The class to which this part belongs.
- 7** For SD-, PC-, and CM-type entries, this field contains the following flags:
- Bit 2: 0 = use the RMODE bit (5)  
1 = RMODE is 64
  - Bit 3: 0 = use the AMODE bits (6-7)  
1 = AMODE is 64
  - Bit 4: 0 = Section is not an RSECT  
1 = Section is an RSECT
  - Bit 5: 0 = RMODE is 24  
1 = RMODE is 31
  - Bits 6-7: 00 = AMODE is 24  
01 = AMODE is 24  
10 = AMODE is 31  
11 = AMODE is ANY
- 8** When symbol **1** is defined in an ALIAS instruction, this field shows the name of the external dummy section, control section, entry point, part or external symbol of which symbol **1** is an alias.

---

## Source and object

This section of the listing documents the source statements of the module and the resulting object code.

This section is the most useful part of the listing because it gives you a copy of all the statements in your source program (except listing control statements) exactly as they are entered into the machine. You can use it to find simple coding errors, and to locate and correct errors detected by the assembler. By using this section with the Ordinary Symbol and Literal Cross Reference section, you can check that your branches and data references are in order. The location counter values and the object code listed for each statement help you locate any errors in a storage dump. Finally, you can use this part of the listing to check that your macro instructions have been expanded properly.

On z/OS and CMS, the assembler can produce two formats of the Source and Object section: a 121-character format and a 133-character format. To select one,

you must specify either the LIST(121) assembler option or the LIST(133) assembler option. Both sections show the source statements of the module, and the object code of the assembled statements.

The 133-character format shows the location counter, and the first and second operand addresses (ADDR1 and ADDR2) as 8-byte fields in support of 31-bit addresses. This format is required when producing the generalized object format data set (see “GOFF (z/OS and CMS)” on page 57). The 133-character format also contains the first eight characters of the macro name in the identification-sequence field for statements generated by macros. Figure 3 shows an example of the Source and Object section of the listing. This section shows the source statements of the module, and the object code of the assembled statements.

High Level Assembler lets you write your program, and print the assembler listing headings, in mixed-case. Diagnostic messages are printed in the language you specify in the LANGUAGE assembler option described in “LANGUAGE” on page 60.

Figure 3 shows an example of the Source and Object section in 121-character format, and in mixed-case.

---

<b>1</b>	<b>2</b>											Page	3
SAMP01 Sample Listing Description													
Active Usings: None													
<b>3</b>	<b>4</b>	<b>5</b>	<b>6</b>	<b>7</b>						<b>8</b>	<b>9</b>		
Loc	Object	Code	Addr1	Addr2	Stmt	Source	Statement	HLASM R6.0			2008/07/11 17.48		
000000			00000	000E0	2	Samp01	Csect						
					22	Entry1	SAMPMAC Parm1=YES				00002300		
000000	18CF				23+	Entry1	LR 12,15				01-SAMPM		
					24+	ENTRY	Entry1				01-SAMPM		
<b>12</b>													
			R:C	00000	25+	USING	Entry1,12	Ordinary	Using		01-SAMPM		
000002	0000	0000		00000	26+	LA	Savearea,10				01-SAMPM		
<b>10</b>	** ASMA044E Undefined symbol - Savearea												
<b>10</b>	** ASMA029E Incorrect register specification - Savearea												
<b>11</b>	** ASMA435I Record 6 in SAMP01 MACLIB A1(SAMPMAC) on volume: EAR191												
000006	50D0	A004		00004	27+	ST	13,4(,10)				01-SAMPM		
00000A	50A0	D008		00008	28+	ST	10,8(,13)				01-SAMPM		
00000E	18DA				29+	LR	13,10				01-SAMPM		
			R:A35	00010	30+	USING	*,10,3,5	Ordinary	Using,Multiple Base		01-SAMPM		
** ASMA303W Multiple address resolutions may result from this USING and the USING on statement number 25													
<b>13</b>	** ASMA435I Record 10 in SAMP01 MACLIB A1(SAMPMAC) on volume: EAR191												
					31+	DROP	10,3,5	Drop Multiple	Registers		<b>14</b>		
					32	COPY	SAMPLE				01-SAMPM		
					33=*	Line from member SAMPLE					00002400		
	C 02A	00000	0002A		34	Using	IHADCB,INDCB	Establish	DCB addressability		00002500		
	C 07A	00000	0007A		35	Using	IHADCB,OUTDCB				00002600		
					36	push	using				00002700		
<b>15</b>													
	R:2	00000			37	PlistIn	Using Plist,2	Establish	Plist addressability		00002800		
	R:3	00000			38	PlistOut	Using Plist,3				00002900		
SAMP01 Sample Listing Description													
<b>16</b>	Active Usings (1):Entry1,R12 IHADCB(X'FD6'),R12+X'2A' PlistIn.plist,R2 PlistOut.plist,R3												
ODCB,IHADCB(X'F86'),R12+X'7A'													
Loc	Object	Code	Addr1	Addr2	Stmt	Source	Statement	HLASM R6.0			2008/07/11 17.48		
000010	1851				40	?Branch	LR R5,R1	Save	Plist pointer		00003100		
** ASMA147E Symbol too long, or first character not a letter - ?Branch													
** ASMA435I Record 30 in SAMP01 ASSEMBLE A1 on volume: EAR191													
000012	5820	5000		00000	41	L	R2,0(,R5)	R2 = address of request list			00003200		
000016	47F0	C022		00022	42	B	Open				00003300		
					697	End					00055100		
0000D0	00000001				698		=f'1'						
0000D4	00000000				699		=V(RCNVDAT)						
0000D8	00000000				700		=V(RCNVTIME)						
0000DC	00000002				701		=f'2'						

---

Figure 3. Source and object listing section—121 format

**1** The deck identification, if any, consisting of 1–8 characters. It is obtained

from the name field of the first named TITLE statement. The assembler prints the deck identification and date on every page of the listing except the Options Summary.

- 2** The information taken from the operand field of a TITLE statement.
- 3** Location field. This is the value of the location counter that represents the assembled address (in hexadecimal notation) of the object code.
  - For ORG statements, the value of the location counter before the ORG is placed in the location column, and the value of the location counter after the ORG is placed in the Addr2 field.
  - If the END statement contains an operand, the operand value (requested entry point) appears in the location field.
  - In the case of LOCTR, COM, CSECT, RSECT, and DSECT statements, the location field contains the current address of these control sections.
  - In the case of EXTRN, WXTRN, ENTRY, and DXD instructions, the location field and object code field are blank.
  - For LTORG statements, the location field contains the location assigned to the literal pool.

If, at the time of the page eject, the current control section being assembled is a COM section, the heading line starts with C-LOC. If, at the time of the page eject, the current control section being assembled is a DSECT, the heading line starts with D-LOC. If, at the time of the page eject, the current control section being assembled is an RSECT, the heading line starts with R-LOC.

- 4** The object code produced by the source statement. The entries, which are shown left-justified and in hexadecimal notation, are machine instructions or assembled constants. Machine instructions are printed in full with a space inserted after every 4 digits (2 bytes). Only the first 8 bytes of a constant appears in the listing if PRINT NODATA is in effect, unless the statement has continuation records. The whole constant appears if PRINT DATA is in effect. (See “PRINT instruction” in the *HLASM Language Reference*.)

This field also shows the base registers for ordinary USING instructions, and the base register and displacement for dependent USING instructions. See **12** and **15** for more details.

- 5** Effective addresses (each the result of adding a base register value and a displacement value):
  - The field headed Addr1 contains the effective address for the first operand of an instruction (if applicable). It may also contain the following:
    - For a USING instruction, the Addr1 field contains the value of the first operand.
    - For a CSECT, START, LOCTR, or RSECT instruction, the Addr1 field contains the start address of the control section.
    - For an ORG instruction, the Addr1 field contains the value of the location counter before the ORG.
    - For an EQU instruction, the Addr1 field contains the value assigned.
  - The field headed Addr2 contains the effective address of the last operand of any instruction referencing storage.
    - For a USING instruction, the Addr2 field contains the value of the second operand.

- For a CSECT, START, LOCTR, or RSECT instruction, the Addr2 field contains the end address of the control section.
- For an ORG instruction, the Addr2 field contains the next address as specified by the operand field.
- For an EQU instruction, the Addr2 field contains the length assigned.

If the assembler option LIST(121) is in effect, both address fields contain 6 digits; however, if the high-order digit is 0, it is not printed. If the assembler option LIST (133) is in effect, both address fields contain 8 digits. For USING and EQU instructions, the Addr2 field may contain up to 8 digits.

**6**

The statement number. The column following the statement number may contain the following values:

- A plus sign (+) indicates that the statement was generated as the result of macro call processing.
- An unnumbered statement with a plus sign (+) is the result of open code substitution.
- A minus sign (–) indicates that the statement was read by a preceding AREAD instruction.
- An equals sign (=) indicates that the statement was included by a COPY instruction.
- A greater-than sign (>) indicates that the statement was generated as the result of a preceding AINSERT instruction. If the statement is read by an AREAD instruction, this will take precedence and a minus sign will be printed.

**7**

The source program statement. The following items apply to this section of the listing:

- Source statements are listed, including those brought into the program by the COPY assembler instruction, and including macro definitions submitted with the main program for assembly. Listing control instructions are not printed, except for PRINT, which is printed unless the NOPRINT operand is specified.
- Macro definitions obtained from a library are not listed, unless the macro definition is included in the source program by means of a COPY statement, or the LIBMAC assembler option was specified.
- The statements generated as the result of a macro instruction follow the macro instruction in the listing, unless PRINT NOGEN is in effect. If PRINT GEN is in effect and PRINT NOMSOURCE is specified, the printing of the source statements generated during macro processing and conditional assembly substitution is suppressed, without suppressing the printing of the generated object code of the statements. If PRINT MCALL is in effect, nested macro instructions including all parameters are printed. When the PRINT NOGEN instruction is in effect, the assembler prints one of the following on the same line as the macro call or model statement:
  - The object code for the first instruction generated
  - The first 8 bytes of generated data from a DC instruction

When the assembler forces alignment of an instruction or data constant, it generates zeros in the object code and prints only the generated object code in the listing. When you use the PRINT NOGEN instruction the generated zeros are not printed.

## Source and object

**Diagnostic Messages and Generated Data:** If the next line to print after a macro call or model statement is a diagnostic message, the generated data is not shown.

- Assembler and machine instruction statements in the source program that contain variable symbols are listed twice: first, as they appear in the source input, and second, with values substituted for the variable symbols. See Figure 4 for an example of this.
- All error diagnostic messages appear in line except those suppressed by the FLAG option. Chapter 6, “Diagnosing assembly errors,” on page 153 describes how error messages and MNOTEs are handled.
- Literals that have not been assigned locations by LTORG statements appear in the listing following the END statement. Literals are identified by the equal sign (=) preceding them.
- Whenever possible, a generated statement is printed in the same format as the corresponding macro definition (model) statement. The starting columns of the operation, operand, and comments fields are preserved, unless they are displaced by field substitution, as shown in Figure 4.

Loc	Object	Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11 17.48
					1	&A SETC 'abcdefghijklmnp'		00001000
					2	&A LA 4,1 Comment		00002000
000000	4140	0001		00001		+abcdefghijklmnp LA 4,1		X00002000
						+ Comment		
					3	&b SETC 'abc'		00003000
					4	&b LA 4,1 Comment		00004000
000004	4140	0001		00001		+abc LA 4,1 Comment		00004000

Figure 4. Source and object listing section

It is possible for a generated statement to occupy ten or more continuation lines on the listing. In this way, generated statements are unlike source statements, which are restricted to nine continuation lines.

- 8** The release level of High Level Assembler.
- 9** The date and time at the start of the assembly.
- 10** The error diagnostic messages immediately follow the source statement in error. Many error diagnostic messages include the segment of the statement that is in error. You can use the FLAG assembler option to control the level of diagnostic messages displayed in your listing.
- 11** The informational message, ASMA435I, that describes the origin of the source statement in error. This message is only printed when you specify the FLAG(RECORD) assembler option.

If the input data set containing the source in error is a USS file, message ASMA435I may continue over more than one print line. If the inclusion of the path name in the message causes the message to be more than 255 bytes in length, the message is truncated.

---

Loc	Object Code	Addr1	Addr2	Stmt	Source	Statement	
000004	5810 0001		00001	6	1	1,1	HLASM R6.0 2008/07/11 17.48
** ASMA309W Operand 1 resolved to a displacement with no base register							
** ASMA033I Storage alignment for 1 unfavorable							
** ASMA435I Record 6 in /u/carland/assembler/source/dataset.which/has/a.very/longname/thus/causing/this/message/tobe/printed/OVER/more/than/one/line/ on volume:							

---

Figure 5. Example showing truncation of long ASMA435I message

- 12** The Addr1 and Addr2 columns show the first and second operand addresses in the USING instructions. The base registers on an ordinary USING instruction are printed, right justified in the object code columns, preceded by the characters "R:".
- 13** A second instance of the informational message ASMA435I (also mentioned in **11**). Conditional assembly statements and comment statements contribute to the record count of macro definitions, as suggested by the record number which is greater than the number of generated statements.
- 14** The identification-sequence field from the source statement. For a macro-generated statement, this field contains information identifying the origin of the statement. The first two columns define the level of the macro call, where a level of 01 indicates statements generated by the macro specified within the source code, and higher level numbers indicate statements generated from macros invoked from within a macro.

For a library macro call, the last five columns contain the first five characters of the macro name. For a macro whose definition is in the source program (including one read by a COPY statement or by the LIBMAC assembler option), the last five characters contain the line number of the model statement in the definition from which the generated statement is derived. This information can be an important diagnostic aid in analyzing output resulting from macro calls within macro calls.

- 15** The Addr1 and Addr2 columns show the first and second operand addresses in the USING instructions. The resolved base displacement for a dependent USING instruction is printed in the object code columns, as *register displacement*, where *register* is shown as a hexadecimal value.
- 16** The current USING PUSH level is printed after the heading and before the first active USING. If the USING PUSH level is zero, it is not shown.

If PRINT UHEAD or PCONTROL(UHEAD) has been specified, a summary of current active USINGs is printed on up to four heading lines, following the TITLE line on each page of the source and object section. The USINGs listed are those current at the end of the assembly of the last statement on the previous page of the listing, with the following exceptions:

- The USINGs summary shows the effect of the USING instruction when:
  - It is the first statement in the source input data set, or
  - It is the first statement on the new page
- The USINGs summary shows the effect of the DROP instruction when:
  - It is the first statement in the source input data set, or
  - It is the first statement on the new page

Current active USINGs include USINGs that are temporarily overridden. In the following example the USING for base register 12 temporarily overrides the USING for base register 10. After the DROP instruction, the base register for BASE1 reverts to register 10.



## Source and object

```
USING BASE1,10
USING BASE1,12      Temporarily overrides register 10
LA    1,BASE1       Uses base register 12
DROP  12
LA    1,BASE1       Uses base register 10
```

The summary of active USINGs heading lines have the format:

Active Usings (n): *label.sectname+offset(range),registers*

where:

<b>n</b>	Is the current PUSH level. If the PUSH level is zero, it is not shown. If no USING statements are active, the heading appears as Active Usings: None.
<i>label</i>	Is the label name specified for a Labeled USING. If the USING is not labeled, this field is omitted.
<i>sectname</i>	Is the section name used to resolve the USING. The section name is listed as (PC) if the section is an unnamed CSECT, (COM) if the section is unnamed COMMON, and (DSECT) if the section is an unnamed DSECT.
<i>offset</i>	Is the offset from the specified section that is used to resolve the USING. This field is omitted if it is zero.
<i>(range)</i>	Is the number of bytes addressed by this base register for instructions with 12-bit displacement fields. It is only shown if the default value (any multiple of X'1000') is not used.
<i>registers</i>	<p>Is the register or registers specified on the USING statement.</p> <p>For dependent USINGs, the register is printed as <i>register+offset</i> where <i>register</i> is the register used to resolve the address from the corresponding ordinary USING, and <i>offset</i> is the offset from the register to the address specified in the dependent USING.</p>

If there are more active USINGs than can fit into four lines, the summary is truncated, and the character string 'MORE ...' is appended to the last line.

In Figure 6, the USINGs at statements 25 and 30 are ordinary USINGs. The USING at statement 34 is a dependent USING, and that at statement 35 is a labeled dependent USING. The USINGs at statements 37 and 38 are labeled USINGs.

Figure 6 also shows an example of the *Source and Object* section when the same assembly is run with assembler option LIST(133), and is followed by a description of differences with respect to Figure 3 on page 15:



SAMP01 Sample Listing Description									
Active Usings: None									
Page 3									
1	Loc	Object Code	Addr1	Addr2	Stmt	Source	Statement	HLASM R6.0	2008/07/11 17.48
	00000000		00000000	000000E0	2	Samp01	Csect		
					22	Entry1	SAMPMAC Parm1=YES		00002300
	00000000	18CF			23+	Entry1	LR 12,15		01-SAMPMAC
					24+		ENTRY Entry1		01-SAMPMAC
			2						
			R:C 00000000		25+		USING Entry1,12	Ordinary Using	01-SAMPMAC
	00000002	0000 0000		00000000	26+		LA Savearea,10		01-SAMPMAC
	** ASMA044E Undefined symbol - Savearea								
	** ASMA029E Incorrect register specification - Savearea								
	** ASMA435I Record 6 in SAMP01 MACLIB A1(SAMPMAC) on volume: EAR191								
	00000006	50D0 A004		00000004	27+		ST 13,4(,10)		01-SAMPMAC
	0000000A	50A0 D008		00000008	28+		ST 10,8(,13)		01-SAMPMAC
	0000000E	18DA			29+		LR 13,10		01-SAMPMAC
								3	
			R:A35 00000010		30+		USING *,10,3,5	Ordinary Using,Multiple Base	01-SAMPMAC
	** ASMA303W Multiple address resolutions may result from this USING and the USING on statement number 25								
	** ASMA435I Record 10 in SAMP01 MACLIB A1(SAMPMAC) on volume: EAR191								
					31+		DROP 10,3,5	Drop Multiple Registers	01-SAMPMAC
					32		COPY SAMPLE		00002400
					33=*		Line from member SAMPLE		
	C 02A	00000000	0000002A		34		Using IHADCB,INDCB	Establish DCB addressability	00002500
	C 07A	00000000	0000007A		35	ODCB	Using IHADCB,OUTDCB		00002600
					36		push using		00002700
	R:2	00000000			37	PlistIn	Using Plist,2	Establish Plist addressability	00002800
	R:3	00000000			38	PlistOut	Using Plist,3		00002900
SAMP01 Sample Listing Description									
Active Usings (1):Entry1,R12 IHADCB(X'FD6'),R12+X'2A' PlistIn.plist,R2 PlistOut.plist,R3									
ODCB.IHADCB(X'F86'),R12+X'7A'									
Page 4									
	Loc	Object Code	Addr1	Addr2	Stmt	Source	Statement	HLASM R6.0	2008/07/11 17.48
	00000010	1851			40	?Branch	LR R5,R1	Save Plist pointer	00003100
	** ASMA147E Symbol too long, or first character not a letter - ?Branch								
	** ASMA435I Record 30 in SAMP01 ASSEMBLE A1 on volume: EAR191								
	00000012	5820 5000		00000000	41	L	R2,0(,R5)	R2 = address of request list	00003200
	00000016	47F0 C022		00000022	42	B	Open		00003300
					697		End		00055100
	000000D0	00000001			698		=f'1'		
	000000D4	00000000			699		=V(RCNVDAT)		
	000000D8	00000000			700		=V(RCNVTIME)		
	000000DC	00000002			701		=f'2'		

Figure 6. Source and object listing section—133 format

- 1 The Addr1 and Addr2 columns show 8-character operand addresses.
- 2 The assembled address of the object code occupies 8 characters.
- 3 The first 8 characters of the macro name are shown in the identification-sequence field.

## Relocation dictionary (RLD)

This section of the listing describes the relocation dictionary information passed to the linkage editor or loader, or z/OS binder, in the object module.

The entries describe the address constants in the assembled program that are affected by relocation. This section helps you find relocatable constants in your program.

**Note:** The Relocation dictionary listing shown in Figure 7 on page 22 is not related to the program segment shown in Figure 6.

---

TSSC004					Relocation Dictionary	Page 6
<b>1</b>	<b>2</b>	<b>3</b>	<b>4</b>	<b>5</b>		
Pos.Id	Rel.Id	Address	Type	Action		
00000003	00000002	00000000	J 4	ST	HLASM R6.0	2008/07/11 17.48
00000003	00000005	0000001C	RI 2	+		
00000003	00000005	00000020	A 4	+		
00000003	00000005	00000026	RI 2	+		
00000003	00000006	0000005A	RI 4	-		
00000003	00000006	00000060	A 4	-		
00000003	00000007	0000005A	RI 4	+		
00000003	00000007	00000060	A 4	+		
00000003	00000002	00000000	J 4	ST		
00000003	00000002	0000006C	V 4	ST		

---

Figure 7. Relocation dictionary (RLD) listing

- 1** The external symbol directory ID (in hexadecimal notation) of the element or part within which this address constant resides.
- 2** The external symbol directory ID (in hexadecimal notation) of the element or part which will be used as the basis for relocation.
- 3** The assembled address (in hexadecimal notation) of the field where the address constant is stored.
- 4** The type and length of the address constant. The type may contain the following values:
  - A** A-type address constant
  - V** V-type address constant
  - Q** Q-type address constant
  - J** J-type address constant or CXD instruction
  - R** R-type address constant
  - RI** Relative Immediate offset
- 5** The relocation action which may contain the following values:
  - +** The relocation operand is added to the address constant
  - The relocation operand is subtracted from the address constant
  - ST** The relocation operand overwrites the address constant

---

## Ordinary symbol and literal cross reference

This section of the listing concerns symbols and literals that are defined and used in the program.

Ordinary Symbol and Literal Cross Reference										Page 20									
1	2	3	4	5	6	7	8	9	10										
Symbol	Length	Value	Id	R	Type	Asm	Program	Defn	References	HLASM R6.0	2008/07/11	17.48							
DCBBIT0	1	00000080	FFFFFFFF	A	U			68	101 109 122 146 179	181 182 184 207 210 230 234									
DCBBIT1	1	00000040	FFFFFFFF	A	U			69	102 110 124 147 148 157 163 179	181 183 184 212									
DCBBIT2	1	00000020	FFFFFFFF	A	U			70	103 111 125 126 127 147 148 152 158 163 179	180									
DCBBIT3	1	00000010	FFFFFFFF	A	U			71	104 125 127 128 147 160 186 217 235 238 261 262										
DCBBIT4	1	00000008	FFFFFFFF	A	U			72	112 161 162 163 187 218 240 245 246 266 267 301										
DCBBIT5	1	00000004	FFFFFFFF	A	U			73	113 168 190 191 220 240 242 243 246 270 272 273										
DCBBIT6	1	00000002	FFFFFFFF	A	U			74	105 169 170 173 190 192 221 277 278 279 280 314										
DCBBIT7	1	00000001	FFFFFFFF	A	U			75	106 169 171 173 194 225 282 283 320 321 323 324										
Entry1	2	00000000	00000003	I				23	24 25U										
IHADCB	1	00000000	FFFFFFFF	J				56	34U 35U 83 132 203 328 335 353										
INDCB	2	0000002A	00000003	H	H			46	34U										
Open	2	00000022	00000003	H	H			366	42B										
OUTDCB	2	0000007A	00000003	H	H			48	35U										
plst	1	00000000	FFFFFFFF	J				360	37U 38U										
RCNVDAT	1	00000000	0000000D	T				699	699										
RCNVTIME	1	00000000	0000000E	T				700	700										
r1	1	00000001	00000003	A	U			369	40										
r2	1	00000002	00000003	A	U			370	41M										
r5	1	00000005	00000003	A	U			373	40M 41										
Samp01	1	00000000	00000003	J				2	20 45 47 356 363 365										
Savearea	***UNDEFINED***	00000000	A	U				26											
=f'1'	4	000000D0	00000003	F				698	396										
=f'2'	4	000000DC	00000003	F				701	400										
=V(RCNVDAT)	4	000000D4	00000003	V				699	397										
=V(RCNVTIME)	4	000000D8	00000003	V				700	399										

Figure 8. Ordinary symbol and literal cross reference

- Shows each symbol or literal. Symbols are shown in the form in which they are defined, either in the name entry of a machine or assembler instruction, or in the operand of an EXTRN or WXTRN instruction. Symbols defined using mixed-case letters are shown in mixed-case letters, unless the FOLD assembler option was specified.

If a symbol name is used as a literal more than once in a program, and the form of the symbol name is coded differently, for example =V(symbol) and =V(SYMBOL), and the symbol is not defined in the program, the symbol is listed in the form of the first reference. In the following example the assembler lists the symbol name as inPUT, because the third statement is the first occurrence of the symbol, and the symbol was not previously defined.

```
test    csect
        using      *,15
        la         1,=v(inPUT)      third statement
        la         1,=v(INPUT)
        end
```

In the following example the assembler lists the symbol name inPUT, because the third statement defines inPUT as an external symbol. The assembler also lists the symbol name INput, because the fifth statement defines INput as an ordinary symbol.

```
test    csect
        using      *,15
        la         1,=v(inPUT)      third statement
        la         1,=v(INPUT)
        INput      dc      c14' '   fifth statement
        END
```

- Shows, in decimal notation, the byte length of the field represented by the symbol. This field is blank for labeled USINGs (see symbol WA).

## Ordinary symbol and literal cross reference

- 3** Shows the hexadecimal address assigned to the symbol or literal, or the hexadecimal value to which the symbol is equated. This field is blank for labeled USING symbols. The Value column may contain the UNDEFINED or QUALIFIER strings, depending on the properties of the symbol.
- 4** For symbols and literals defined in an executable control section or a dummy section, this field shows the external symbol dictionary ID (ESDID) assigned to the ESD entry for the control section in which the symbol or literal is defined. For external symbols, this field indicates the ESDID assigned to ESD entry for this symbol. For symbols defined in a dummy control section, this field indicates the control section ID assigned to the control section. For symbols defined using the EQU statement, if the operand contains a relocatable expression, this field shows the external symbol dictionary ID of the relocatable expression. Otherwise, it contains the current control section ID.
- 5** Column title R is an abbreviation for “Relocatability Type”. Symbols f112nd and WA are absolute symbols and are flagged “A” in the R column. Symbol jix is the result of a complex relocatable expression and is flagged “C” in the R column. Symbol I0error is simply relocatable and is not flagged.
- 6** Indicates the type attribute of the symbol or literal. Refer to “Type attribute (T)” in the *HLASM Language Reference* for details.
- 7** Indicates the assembler type of the symbol, including type extensions (if any). Refer to *HLASM Language Reference* for details.
- 8** Indicates the program type of the symbol. Refer to *HLASM Language Reference* for details.
- 9** Is the statement number in which the symbol or literal was defined.
- 10** Shows the statement numbers of the statements in which the symbol or literal appears as an operand. Additional indicators are suffixed to statement numbers as follows:
- |          |  |
|----------|--|
| <b>B</b> | The statement contains a branch instruction, and the relocatable symbol is used as the branch-target operand address.  |
| <b>D</b> | The statement contains a DROP instruction, and the symbol is used in the instruction operand.  |
| <b>M</b> | The instruction causes the contents of a register represented by an absolute symbol, or a storage location represented by one or more relocatable symbols, to be modified. |
| <b>U</b> | The statement contains a USING instruction, and the symbol is used in one of the instruction operands.   |
| <b>X</b> | The statement contains an EX machine instruction, and the symbol in the second operand is the symbolic address of the target instruction.                                  |

In the case of a duplicate symbol this column contains the message:

\*\*\*\*DUPLICATE\*\*\*\*

A symbol name may appear in the cross reference section as both an external symbol name and an ordinary symbol name. In this situation there is no duplication.

The following notes apply to the cross reference section:

Notes:

- 1. Cross reference entries for symbols used in a literal refer to the assembled literal in the literal pool. Look up the literals in the cross reference to find where the symbols are used.
- 2. A PRINT OFF listing control instruction does not affect the production of the cross reference section of the listing.
- 3. In the case of an undefined symbol, the columns Length ( 2 ) and Value ( 3 ) contain the message:

\*\*\*\*UNDEFINED\*\*\*\*

Unreferenced symbols defined in CSECTs

This section of the listing shows symbols that have been defined in CSECTs but not referenced. This helps you remove unnecessary data definitions, and reduce the size of your program. The list of symbols are shown in symbol name order. To obtain this section of the listing, you need to specify the XREF(UNREFS) assembler option.

SAMP01	Unreferenced Symbols Defined in CSECTs		Page 19
1	2		HLASM R6.0 2008/07/11 17.48
Defn	Symbol		
47	ODCB		
49	PlistIn		
50	PlistOut		
7	R0		
10	R3		
16	Unreferenced_Long_Symbol		

Figure 9. Unreferenced symbols defined in CSECTS

- 1 The statement number that defines the symbol.
- 2 The name of the symbol.

Macro and copy code source summary

This section of the listing shows the names of the macro libraries from which the assembler read macros or copy code members, and the names of the macros and copy code members that were read from each library. This section is useful for checking that you have included the correct version of a macro or copy code member.

SAMP01	Macro and Copy Code Source Summary				Page 27
1	2	3	4		HLASM R6.0 2008/07/11 17.48
Con	Source	Volume	Members		
L1	SAMP01	FAL191	SAMPLE	SAMPMAC	
L2	OSMACRO	MNT190	DCBD	IHERMAC	

Figure 10. Macro and copy code source summary

- 1 Contains a number representing the concatenation order of macro and copy code libraries. (This number is not shown when the Source 2 is "PRIMARY INPUT".) The number is prefixed with "L" which indicates Library. The concatenation value is cross-referenced in the Macro and Copy Code Cross Reference section. If the name is more than 44 characters in

## Macro and copy code source summary

length, the path name of the library is truncated. The truncated path name is suffixed with an ellipsis to indicate that it has been truncated.

- Shows either the name of each library from which the assembler reads a macro or a copy code member or, for in-line macros, the words “PRIMARY INPUT”.

**Note:** The file names in the example are from CMS (not z/OS or z/VSE).

- Shows the volume serial number of the volume on which the library resides.
- Shows the names of the macros or copy members that were retrieved from the library.

You can suppress this section of the listing by specifying the NOMXREF assembler option.

**LIBRARY User Exit:** If a LIBRARY user exit has been specified for the assembly, and the exit opens the library data set, the exit can return the name of the library to the assembler. In this case the *Macro and Copy Code Source Summary* lists the library names returned by the user exit.

## Macro and copy code cross reference

This section of the listing shows the names of macros and copy code members and the statements where the macro or copy code member was called. You can use the assembler option MXREF(XREF) or MXREF(FULL) to generate this section of the listing.

Macro and Copy Code Cross Reference					Page 28
1	2	3	4	5	
Macro	Con	Called By	Defn	References	
A		PRIMARY INPUT	826	971, 973, 998	HLASM R6.0 2008/07/11 17.48
AINsert_TEST_MACRO					
		PRIMARY INPUT	3	16	
AL		PRIMARY INPUT	873	981, 983	
DCBD	L3	PRIMARY INPUT	-	113	
IHBERMAC	L3	DCBD	-	113	
L		PRIMARY INPUT	816	966, 968	
MAC1		PRIMARY INPUT	28	36	
N		PRIMARY INPUT	933	991	
O		PRIMARY INPUT	953	993	
SAMPLE	L1	PRIMARY INPUT	-	85C	6
SAMPMAC	L1	PRIMARY INPUT	-	64	
SAVE	L3	PRIMARY INPUT	-	42	
SL		PRIMARY INPUT	883	986, 988	
ST		PRIMARY INPUT	836	976, 978	
TYPCHKRX		PRIMARY INPUT	745	775, 845, 892	
X		PRIMARY INPUT	943	996	
XIT1	L1	PRIMARY INPUT	-	30C	
XIT2	L2	PRIMARY INPUT	-	32C	
XIT3	L1	PRIMARY INPUT	-	34C	

Figure 11. Macro and copy code cross reference

- The macro or copy code member name.
- Shows the value representing the input source concatenation, as listed in the Macro and Copy Code Source Summary (refer to Figure 10 on page 25) and under the sub-heading “Datasets Allocated for this Assembly” in the Diagnostic Cross Reference and Assembler Summary (refer to Figure 20 on page 33).
- Shows either the name of the macro that calls this macro or copy code

member, or the words “PRIMARY INPUT” indicating the macro or copy code member was called directly from the primary input source. If you use the COPY instruction to copy a macro definition, then references to the macro are shown as called by “PRIMARY INPUT”.

- 4 One of these:
  - The statement number for macros defined in the primary input file,
  - A dash (-) indicating the macro or copy code member was retrieved from a library.
- 5 The statement number that contains the macro call or COPY instruction.

**Lookahead Processing:** If a COPY instruction is encountered during lookahead, this is the number of the statement that causes lookahead processing to commence.

**PCONTROL(MCALL) Assembler Option:** If you specify the PCONTROL(MCALL) assembler option, and you copy a macro definition from an inner macro, the number shown against the copied member is one less than the statement number containing the inner macro call instruction. See “Effects of LIBMAC and PCONTROL(MCALL) options” on page 28 for examples of assemblies using different combinations of the LIBMAC and PCONTROL(MCALL) options.

- 6 Statement numbers have a suffix of “C” when the reference is to a member named on a COPY instruction.

Figure 12 shows the format of the Macro and Copy Code Cross Reference when you specify the assembler option, LIBMAC.

Macro and Copy Code Cross Reference					Page 81
SAMP01	Macro	Con	Called By	Defn References	HLASM R6.0 2008/07/11 17.48
<b>1</b>					
A			PRIMARY INPUT	3667 3812, 3814, 3839	
AINSET_TEST_MACRO			PRIMARY INPUT	3 16	
AL			PRIMARY INPUT	3714 3822, 3824	
DCBD	L3		PRIMARY INPUT	224X 2329	
IHBERMAC	L3	DCBD		2331X 2954	
L			PRIMARY INPUT	3657 3807, 3809	
MAC1			PRIMARY INPUT	28 36	
N			PRIMARY INPUT	3774 3832	
O			PRIMARY INPUT	3794 3834	
SAMPLE	L1		PRIMARY INPUT	- 195C	
SAMPMAC	L1		PRIMARY INPUT	153X 174	
SAVE	L3		PRIMARY INPUT	43X 130	
SL			PRIMARY INPUT	3724 3827, 3829	
ST			PRIMARY INPUT	3677 3817, 3819	
TYPCHKRX			PRIMARY INPUT	3586 3616, 3686, 3733	
X			PRIMARY INPUT	3784 3837	
XIT1	L1		PRIMARY INPUT	- 30C	
XIT2	L2		PRIMARY INPUT	- 32C	
XIT3	L1		PRIMARY INPUT	- 34C	

Figure 12. Macro and copy code cross reference—with LIBMAC option

- 1 The “X” flag indicates the macro was read from a macro library and imbedded in the input source program immediately preceding the invocation of that macro. For example, in Figure 12, you can see that SAMPMAC was called by the PRIMARY INPUT stream from LIBRARY L1, at statement number 174, after being imbedded in the input stream at statement number 153. See “Effects of LIBMAC and PCONTROL(MCALL) options” on page 28 for examples of assemblies using different combinations of the LIBMAC and PCONTROL(MCALL) options.

## Macro and copy code cross reference

You can suppress this section of the listing by specifying the NOMXREF assembler option.

### Effects of LIBMAC and PCONTROL(MCALL) options

When you specify different combinations of the LIBMAC and PCONTROL(MCALL) assembler options to assemble the same source program, the definition statement and reference statement numbers can be different in each assembly listing.

The example that follows shows how these options affect the output from an assembly of the same source program. The source program is coded as follows:

```
MACOUTER
END
```

The assembly of this program uses the following library members:

**MACOUTER:** A macro definition that issues a call to macro MACINNER.

**MACINNER:** A macro definition that copies member COPYCODE.

**COPYCODE:** A member containing an MNOTE instruction.

The following four figures illustrate the effects of using the various combinations of the LIBMAC and PCONTROL(MCALL) assembler options.

Figure 13 shows the output when you specify the LIBMAC and PCONTROL(MCALL) options.

										Page	2
Active Usings: None											
Loc	Object	Code	Addr1	Addr2	Stmnt	Source	Statement			HLASM R6.0	2008/07/11 17.48
					1		MACRO			00001000	
					2		MACOUTER			00002000	
					3		MACINNER			00003000	
					4		MEND			00004000	
					5		MACOUTER			00001000	
					6		MACRO			00001000	
					7		MACINNER			00002000	
					8		COPY COPYCODE			00003000	
					9		MNOTE *, 'MNOTE FROM MEMBER COPYCODE'			00001000	
					10		MEND			00004000	
					11+		MACINNER			01-00003	
					12+*,MNOTE		FROM MEMBER COPYCODE			02-00008	
					13		END			00002000	
This line produced because PCONTROL(MCALL) specified											
										Page	3
Con	Source					Macro and Copy Code Source Summary				HLASM R6.0	2008/07/11 17.48
L1	TEST	MACLIB	A1			Volume	Members				
						ADISK	COPYCODE MACINNER MACOUTER				
										Page	4
Macro and Copy Code Cross Reference										HLASM R6.0	2008/07/11 17.48
Macro	Con	Called By		Defn	References						
COPYCODE	L1	MACINNER		-	8C						
MACINNER	L1	MACOUTER		7X	11						
MACOUTER	L1	PRIMARY INPUT		2X	5						

Figure 13. Assembly with LIBMAC and PCONTROL(MCALL) options

Figure 14 on page 29 shows the output when you specify the LIBMAC and NOPCONTROL options.



							Page	2
Active Usings: None								
Loc	Object Code	Addr1	Addr2	Stmnt	Source	Statement	HLASM R6.0	2008/07/11 17.48
				1		MACRO		00001000
				2		MACOUTER		00002000
				3		MACINNER		00003000
				4		MEND		00004000
				5		MACOUTER		00001000
				6		MACRO		00001000
				7		MACINNER		00002000
				8		COPY COPYCODE		00003000
				9		MNOTE *, 'MNOTE FROM MEMBER COPYCODE'		00001000
				10		MEND		00004000
				11+*,	MNOTE	FROM MEMBER COPYCODE		02-00008
				12		END		00002000
Macro and Copy Code Source Summary							Page	3
Con	Source				Volume	Members	HLASM R6.0	2008/07/11 17.48
L1	TEST	MACLIB	A1		ADISK	COPYCODE MACINNER MACOUTER		
Macro and Copy Code Cross Reference							Page	4
Macro	Con	Called By	Defn	References	HLASM R6.0 2008/07/11 17.48			
COPYCODE	L1	MACINNER	-	8C				
MACINNER	L1	MACOUTER	7X	10				
MACOUTER	L1	PRIMARY INPUT	2X	5				

Figure 14. Assembly with LIBMAC and NOPCONTROL options

Figure 15 shows the output when you specify the NOLIBMAC and PCONTROL(MCALL) options.

							Page	2
Active Usings: None								
Loc	Object Code	Addr1	Addr2	Stmnt	Source	Statement	HLASM R6.0	2008/07/11 17.48
				1		MACOUTER		00001000
				2+		MACINNER		01-MACOU
				3+*,	MNOTE	FROM MEMBER COPYCODE		02-MACIN
				4		END		00002000
Macro and Copy Code Source Summary							Page	3
Con	Source					Volume	Members	HLASM R6.0 2008/07/11 17.48
L1	TEST	MACLIB	A1					ADISK COPYCODE MACINNER MACOUTER
Macro and Copy Code Cross Reference							Page	4
Macro	Con	Called By	Defn	References	HLASM R6.0 2008/07/11 17.48			
COPYCODE	L1	MACINNER	-	1C				
MACINNER	L1	MACOUTER	-	2				
MACOUTER	L1	PRIMARY INPUT	-	1				

Figure 15. Assembly with NOLIBMAC and PCONTROL(MCALL) options

Figure 16 on page 30 shows the output when you specify the NOLIBMAC and NOPCONTROL options.

## DSECT cross reference

Active Usings: None										Page	2
Loc	Object	Code	Addr1	Addr2	Stmt	Source	Statement	HLASM R6.0 2008/07/11 17.48			
					1		MACOUTER	00001000			
					2+*,MNOTE	FROM MEMBER	COPYCODE	02-MACIN			
					3		END	00002000			
Macro and Copy Code Source Summary										Page	3
Con	Source					Volume	Members	HLASM R6.0 2008/07/11 17.48			
L1	TEST	MACLIB	A1			ADISK	COPYCODE MACINNER MACOUTER				
Macro and Copy Code Cross Reference										Page	4
Macro	Con	Called By	Defn	References				HLASM R6.0 2008/07/11 17.48			
COPYCODE	L1	MACINNER	-	1C							
MACINNER	L1	MACOUTER	-	1							
MACOUTER	L1	PRIMARY INPUT	-	1							

Figure 16. Assembly with NOLIBMAC and NOPCONTROL options

## DSECT cross reference

This section of the listing shows the names of all internal or external dummy sections defined in the program, and the number of the statement where the definition of the dummy section began.

Dsect Cross Reference				Page	26
<b>1</b>	<b>2</b>	<b>3</b>	<b>4</b>	HLASM R6.0 2008/07/11 17.48	
Dsect	Length	Id	Defn		
AXPRIL	0000003C	FFFFFFFFD	655		
AXPSIL	00000410	FFFFFFFC	771		
AXPXITP	00000014	FFFFFFFE	641		
IHADCB	00000060	FFFFFFFB	799		
Statement					
	00000050	FFFFFFFA	1370		
WORKAREA	000001A8	FFFFFFF	595		

Figure 17. DSECT cross reference

- 1** Shows the name of each dummy section defined in your program.
- 2** Shows, in hexadecimal notation, the assembled byte length of the dummy section.
- 3** For external dummy sections, this field indicates the external symbol dictionary ID assigned to the ESD entry for the external dummy section. For internal dummy sections, this field indicates the control section ID assigned to the dummy control section. You can use this field in conjunction with the ID field in the Ordinary Symbol and Literal Cross Reference (see Figure 8 on page 23) to relate symbols to a specific section.
- 4** Shows the number of the statement where the definition of the dummy section began.

You can suppress this section of the listing by specifying the NODXREF assembler option.

## USING map

This section of the listing shows a summary of the USING, DROP, PUSH USING, and POP USING instructions used in your program.

Using Map										Page 27	
										HLASM R6.0 2008/07/11 17.48	
1	2	3	4	5	6	7	8	9	10	11	12
Stmt	Location	Id	Action	Type	Value	Range	Id	Reg	Max	Last	Label and Using Text
Count								Disp		Stmt	
170	00000000	00000001	USING	ORDINARY	00000000	00001000	00000001	15	0002A	171	asmxiniv,r15
175	00000030	00000001	DROP					15			r15
185	00000034	00000001	USING	ORDINARY	00000000	00001000	00000001	12	00000		asmxiniv,r12
186	00000034	00000001	USING	ORDINARY	00000000	00001000	FFFFFFFFD	7	00034	508	axpril,r07
187	00000034	00000001	USING	ORDINARY	00000000	00001000	FFFFFFFA	8	00048	464	Statement,r08
188	00000034	00000001	USING	ORDINARY	00000000	00001000	FFFFFFFC	10	00404	474	axpsil,r10
189	00000034	00000001	USING	ORDINARY	00000000	00001000	FFFFFFFB	11	00052	465	ihadcb,r11
190	00000034	00000001	USING	ORDINARY	00000000	00001000	00000001	12	00589	519	asmxiniv,r12
202	0000004E	00000001	USING	LABELED	00000000	00001000	FFFFFFF	1	00000		WA.WorkArea,r01
203	0000004E	00000001	USING	LAB+DEPND	+0000014A	00000EB6	FFFFFFFB	1			local.ihadcb,WA.mydcb
204	0000004E	00000001	PUSH								
205	00000054	00000001	DROP					1			local
212	0000006A	00000001	POP					1			WA
213	0000006A	00000001	USING	ORDINARY	00000000	00001000	FFFFFFF	13	0014A	527	WorkArea,r13
214	0000006A	00000001	USING	ORDINARY	00000000	00001000					

Figure 18. USING map

- 1** Shows the number of the statement that contains the USING, DROP, PUSH USING, or POP USING instruction.
- 2** Shows the value of the location counter when the USING, DROP, PUSH USING, or POP USING statement was encountered.
- 3** Shows the value of the ESDID of the current section when the USING, DROP, PUSH USING or POP USING statement was encountered.
- 4** Shows whether the instruction was a USING, DROP, PUSH, or POP instruction.
- 5** For USING instructions, this field indicates whether the USING is an ordinary USING, a labeled USING, a dependent USING, or a labeled dependent USING.
- 6** For ordinary and labeled USING instructions, this field indicates the base address specified in the USING. For dependent USING instructions, this field is prefixed with a plus sign (+) and indicates the hexadecimal offset of the address of the second operand from the base address specified in the corresponding ordinary USING.
- 7** Shows the range of the USING. For more information, see “USING instruction” in the *HLASM Language Reference*.
- 8** For USING instructions, this field indicates the ESDID of the section specified on the USING statement.
- 9** For ordinary and labeled USING instructions, and for DROP instructions, this field indicates the register or registers specified in the instruction. There is a separate line in the USING map for each register specified in the instruction. If the DROP instruction has no operands, all registers and labels are dropped and this field contains two asterisks (\*\*).  
  
For dependent USING instructions, the field indicates the register for the corresponding ordinary USING instruction that is used to resolve the address. If the corresponding ordinary USING instruction has multiple registers specified, only the first register used to resolve the address is displayed.
- 10** For each base register specified in an ordinary USING instruction or a labeled USING instruction, this field shows the maximum displacement

calculated by the assembler when resolving symbolic addresses into base-displacement form using that base register.

**11** For ordinary and labeled USING instructions, this field indicates the statement number of the last statement that used the specified base register to resolve an address. Where an ordinary USING instruction is used to resolve a dependent USING, the statement number printed reflects the use of the register to resolve the dependent USING.

**12** For USING and DROP instructions, this field lists the text specified on the USING or DROP instruction, truncated if necessary. For labeled USING instructions, the text is preceded by the label specified for the USING.

If a DROP instruction drops more than one register or labeled USING, the text for each register or labeled USING is printed on the line corresponding to the register that is dropped.

You can suppress this section of the listing by specifying either of the assembler options, USING(NOMAP) or NOUSING.

## General Purpose Register cross reference

This section of the listing shows all references in the program to each of the general registers. Additional flags indicate the type of reference. This is a useful tool in checking the logic of your program; it helps you see if your use of registers is in order.

General Purpose Register Cross Reference																Page	8	
Register	References (M=modified, B=branch, U=USING, D=DROP, N=index)															HLASM R6.0	2008/07/11 17.48	
<b>1</b>	<b>2</b>																	
0(0)	115																	
1(1)	118	120	121	122	124	126	127	128	130	131	133	135	136	137				
2(2)	36	37	38	39	40	41	42	43	44M	45	46	47	48	49	50	51		
	52M	53	54	55M	56	57	58	59M	60	61	62	63	64	65	66	67		
	68	69	70	71	72M	73	74	75	76	77	78	79	80	81	82	83		
	84	85	86	87	88	89M	90	91	92	93M	94	95	96	97	98	99		
	100	101	102	103	104	105	106	107	108	109	110	111	112					
3(3)	(no references identified)															<b>3</b>		
4(4)	16M	281																
5(5)	283																	
6(6)	66N	167N	170	171	174	178	180N	190	192	193	194	197	199	200	201N			
7(7)	283																	
8(8)	283																	
9(9)	224	225	226	227														
10(A)	255U	342D																
11(B)	237	238	239N	240	241	242	243N	244	245N	271								
12(C)	8U																	
13(D)	261	262	263	264	265	266												
14(E)	209	210	211	212	213	214	215	216										
15(F)	34	144																

Figure 19. General Purpose Register cross reference

- 1** Lists the sixteen general registers (0–15).
- 2** The statements within the program that reference the register. Additional indicators are suffixed to the statement numbers as follows:
  - (space) Referenced
  - M** Modified
  - B** Used as a branch address
  - U** Used in USING statement
  - D** Used in DROP statement

N Used as an index register

- 3** The assembler indicates when it has not detected any references to a register.

**Note:** The implicit use of a register to resolve a symbol to a base and displacement does not create a reference in the General Purpose Register Cross Reference.

## Diagnostic cross reference and assembler summary

This section of the listing summarizes the error diagnostic messages issued during the assembly, and provides statistics about the assembly.

The sample listing shown in Figure 20 contains a combination of z/OS and CMS data sets to show examples of the differences in data set information.

**Note:** For a complete list of the diagnostic messages issued by the assembler, see Appendix G, “High Level Assembler messages,” on page 335.

```

Diagnostic Cross Reference and Assembler Summary
Page 9
HLASM R6.0 2008/07/11 17.48

Statements Flagged
1
1(P1,0), 3(P1,3), 4(P1,4), 5(P1,5), 6(P1,6), 7(P1,7), 8(P1,8), 170(L3:DCBD,2149)

2 8 Statements Flagged in this Assembly 16 was Highest Severity Code
High Level Assembler, 5696-234, RELEASE 6.0
SYSTEM: CMS 16 JOBNAME: (NOJOB) STEPNAME: (NOSTEP) PROCSTEP: (NOPROC) 4
Datasets Allocated for this Assembly 5
Con DDname Data Set Name Volume Member
A1 ASMAOPT XITDIS OPTIONS A1 ADISK
P1 SYSIN XITDIS ASSEMBLE A1 ADISK
L1 SYSLIB TEST MACLIB A1 ADISK
L2 DSECT MACLIB A1 ADISK
L3 OSMACRO MACLIB S2 MNT190
L4 OSMACRO1 MACLIB S2 MNT190
6 SYSLIN XITDIS TEXT A1 ADISK
SYSPRINT XITDIS LISTING A1 ADISK

External Function Statistics 7
----Calls---- Message Highest Function
SETAF SETCF Count Severity Name
3 1 5 22 MSG
1 0 2 8 MSG1
1 0 1 0 MSG2

8
Input/Output Exit Statistics
Exit Type Name Calls ---Records--- Diagnostic
Added Deleted Messages
LIBRARY CTLXIT 258 0 0 2
LISTING ASMAXPRT 195 0 52 0

9
Suppressed Message Summary
Message Count Message Count Message Count Message Count
169 0 306 0 309 0 320 0

10 622K allocated to Buffer Pool,
11 16 Primary Input Records Read 13 3072 Library Records Read 0 Work File Reads
12 1 ASMAOPT Records Read 14 141 Primary Print Records Written 0 Work File Writes
15 2 Punch Records Written 16 0 ADATA Records Written

Assembly Start Time: 12.06.06 Stop Time: 12.06.07 Processor Time: 00.00.00.1771 17
Return Code 016

```

Figure 20. Diagnostic cross reference and assembler summary

- 1** The statement number of a statement that causes an error message, or contains an MNOTE instruction, appears in this list. Flagged statements are shown in either of two formats. When assembler option FLAG(NORECORD) is specified, only the statement number is shown. When assembler option FLAG(RECORD) is specified, the format is: *statement(dsnum:member,record)*, where:

### *statement*

is the statement number as shown in the source and object section of the listing.

*dsnum* is the value applied to the source or library data set, showing the type of input file and the concatenation number. "P" indicates the statement was read from the primary input source, and "L" indicates the statement was read from a library. This value is cross-referenced to the input data sets listed under the sub-heading "Datasets Allocated for this Assembly" **5**.

### *member*

is the name of the macro from which the statement was read. on z/OS, this may also be the name of a partitioned data set member that is included in the primary input (SYSIN) concatenation.

*record* is the relative record number from the start of the data set or member which contains the flagged statement.

- 2** The number of statements flagged, and the highest non-zero severity code of all messages issued. The highest severity code is equal to the assembler return code.

If no statements are flagged, the following statement is printed:

No Statements Flagged in this Assembly

If the assembly completes with a non-zero return code, and there are no flagged statements, it indicates there is a diagnostic message in the Option Summary section of the listing (see Figure 1 on page 9).

For a complete discussion of how error messages and MNOTEs are handled, see Chapter 6, "Diagnosing assembly errors," on page 153.

- 3** The current release of High Level Assembler and the last PTF applied.

- 4** Provides information about the system on which the assembly was run. These are:

- The name and level of the operating system used to run the assembly.
- The jobname for the assembly job. If the jobname is not available, "(NOJOB)" is printed.
- The stepname for the assembly job. If the stepname is not available, "(NOSTEP)" is printed.
- The procedure name for the assembly job. If the procedure name is not available, "(NOPROC)" is printed.

- 5** On z/OS and CMS, all data sets used in the assembly are listed by their standard ddname. The data set information includes the data set name, and the serial number of the volume containing the data set. on z/OS, the data set information may also include the name of a member of a partitioned data set (PDS) or library (PDSE).

If a user exit provides the data set information, then the data set name is the value extracted from the Exit-Specific Information block described in "Exit-Specific Information Block" on page 100.

The "Con" column shows the concatenation value assigned for each input data set. You use this value to cross-reference flagged statements, and macros and copy code members listed in the Macro and Copy Code Cross Reference section.

**z/OScolon;** On z/OS, the data set name for all data sets is extracted from the z/OS job file control block (JFCB). If the data set is a JES2 spool file, for example, the data set name is the name allocated by JES2. If the data set is allocated to DUMMY, or NULLFILE, the data set name is shown as NULLFILE.

**CMS:** On CMS, the data set name is assigned one of the values shown in Table 5.

Table 5. Data set names on CMS

File Allocated To:	Data Set Name
CMS file	The 8-character filename, the 8-character filetype, and the 2-character filemode of the file, each separated by a space. If the data set is a disk file in the Shared File system, the volume serial number contains “** SFS”.
Dummy file (no physical I/O)	DUMMY
Printer	PRINTER
Punch	PUNCH
Reader	READER
Labeled tape file	The data set name of the tape file
Unlabeled tape file	TAP <i>n</i> , where <i>n</i> is a value from 0 to 9, or from A to F.
Terminal	TERMINAL

**z/VSE:** On z/VSE, the data set name is assigned one of the values shown in Table 6.

Table 6. Data set names on z/VSE

File Allocated To:	Data Set Name
Disk	The file-id
Job stream (SYSIPT)	None
Library (Disk). The ddname is shown as *LIB*.	The file-id
Printer	None
Punch	None
Labeled tape file	The file-id of the tape file
Unlabeled tape file	None
Terminal (TERM)	None

**6** Output data sets do not have a concatenation value.

**7** The usage statistics of external functions for the assembly. The following statistics are reported:

**SETAF function calls**

The number of times the function was called from a SETAF assembler instruction.

**SETCF function calls**

The number of times the function was called from a SETCF assembler instruction.

**Messages issued**

The number of times the function requested that a message be issued.

<b>Messages severity</b>	The maximum severity for the messages issued by this function.
<b>Function Name</b>	The name of the external function module.
<b>8</b>	The usage statistics of the I/O exits you specified for the assembly. If you do not specify an exit, the assembler does not produce any statistics. The following statistics are reported: <b>Exit Type</b> The type of exit. <b>Name</b> The name of the exit module as specified in the EXIT assembler option. <b>Calls</b> The number of times the exit was called. <b>Records</b> The number of records added and deleted by the exit. <b>Diagnostic Messages</b> The number of diagnostic messages printed, as a result of exit processing.

All counts are shown right justified and leading zeros are suppressed, unless the count is zero.

- 9** The message number of each message specified for suppression, and the count of the number of times it was suppressed during the assembly.
- 10** The amount of storage allocated to the buffer pool.
- 11** The number of primary input records read by the assembler. This count does not include any records read or discarded by the SOURCE user exit.
- 12** The number of records read from the ASMAOPT file (z/OS and CMS) or the Librarian member (z/VSE) by the assembler.
- 13** The number of records read from the libraries allocated to SYSLIB on z/OS and CMS, or assigned to the Librarian on z/VSE. This count does not include any records read or discarded by the LIBRARY user exit.
- 14** The count of the actual number of records generated by the assembler. If you have used the SPACE *n* assembler instruction, the count may be less than the total number of printed and blank lines appearing in the listing. For a SPACE *n* that does not cause an eject, the assembler inserts *n* blank lines in the listing by generating *n*/3 triple-spaced blank records, rounded to the next lower integer if a fraction results. For a SPACE 2, no blank records are generated. The assembler does not generate a blank record to force a page eject.
- This count does not include any listing records generated or discarded by the LISTING user exit.
- 15** The number of object records written. This count does not include any object records generated or discarded by the OBJECT or PUNCH user exits.
- 16** The number of ADATA records written to the associated data file.
- 17** On z/VSE, the assembly start and stop times in hours, minutes and seconds.
- On z/OS and CMS, the assembly start and stop times in hours, minutes and seconds and the approximate amount of processor time used for the assembly, in hours, minutes, and seconds to four decimal places.



## Diagnostic cross reference and assembler summary

The assembly start time does not include the time used during assembly initialization, which allocates main storage and data sets and processes the assembler invocation parameters. The assembly stop time does not include the time used during assembly termination, which deallocates main storage and data sets.

On z/OS and CMS, High Level Assembler provides a sample listing exit which allows you to suppress the Diagnostic Cross Reference and Assembler Summary. See Appendix J, "Sample LISTING user exit (z/OS and CMS)," on page 403.



---

## Chapter 3. Controlling your assembly with options

High Level Assembler offers a number of optional facilities. For example, you can suppress printing of the assembly listing or parts of the listing, and you can specify whether you want an object module or an associated data file. There are two types of options:

- Simple pairs of keywords: A positive form (such as OBJECT) requests a facility, and an alternate negative form (such as NOOBJECT) excludes the facility.
- Keywords, such as LINECOUNT(50), that permit you to assign a value to a function.

High Level Assembler accepts options from five different sources:

- External file (z/OS and CMS)
- Library member (z/VSE)
- Invocation parameter
- JCL Option (z/VSE)
- \*PROCESS statement

This chapter describes the different sources for assembler options, each assembler option, and when you can use the options. Each option has a default value that the assembler uses if you do not specify an alternative value. The way in which the default values are arrived at is explained under “Default options” on page 42.

---

### The sources of assembler options

This section describes in detail the different sources of assembler options, and the general rules for specifying the options.

Before describing the sources, the section sets out the rules of precedence by which the assembler works out what to do when an option is specified two or more times with differing values.

### Precedence of assembler options

Assembler options are recognized in this order of precedence (highest to lowest):

1. Fixed installation default options
2. Options on \*PROCESS OVERRIDE statements
3. Options in the ASMAOPT file (CMS or z/OS) or library member (z/VSE)
4. Invocation options
  - a. Options on the JCL PARM parameter of the EXEC statement on z/OS and z/VSE, or the ASMAHL command on CMS
  - b. Options on the JCL OPTION statement (z/VSE)
  - c. Options specified via the STDOP (Standard JCL Options) command (z/VSE)
5. Options on \*PROCESS statements
6. Non-fixed installation default options

You can specify an option as often as you want, and in as many sources as you want. However, this may mean that you have specified the positive and negative form of an option (for keyword pairs), or two or more different values (for a value keyword). These option specifications are “conflicting” options. If all specifications of a particular option are at the same level of precedence, the last specification takes effect, and a warning message is issued. If some conflicting specifications are

## Precedence of assembler options

at different levels of precedence, then the specification at the higher order of precedence takes effect, and (in general) the assembler issues a warning message for each option that is not accepted. A warning message is not issued if the higher level of precedence is a \*PROCESS OVERRIDE statement, unless the option cannot be set by a \*PROCESS statement.

### Fixed installation default options

If an option was specified on the DELETE operand of the ASMAOPT macro during installation, you cannot change the option when you invoke the assembler.

### \*PROCESS OVERRIDE Statement Options

If the keyword OVERRIDE is added to a process (\*PROCESS) statement, then the nominated assembler option is not overridden by specifications at a lower level of precedence. Furthermore, if there is a conflicting specification at a lower level of precedence, the assembler does *not* issue a warning message.

If an option specified on the process statement is an option listed in “\*PROCESS statement options” on page 41, and a different value is supplied as an ASMAOPT or invocation option, then the ASMAOPT or invocation value is accepted, and the assembler issues a warning message.

### ASMAOPT options

High Level Assembler accepts options from an external file (z/OS and CMS) with the DDname ASMAOPT or library member (z/VSE) with the name and type ASMAOPT.USER. The file or library member may contain multiple records. All records are read from the file or library member.

The contents of each record are used to build an internal buffer containing the complete option list. Each record is processed until the first space is encountered, unless the option being processed is a SYSPARM option which is enclosed in quotes. The assembler appends the options string from each record, separating the strings with commas. For example, these records:

```
ADATA,MXREF  
SYSPARM(TESTPARM)  
XREF(FULL)
```

generate this option list:

```
ADATA,MXREF,SYSPARM(TESTPARM),XREF(FULL)
```

### Invocation options

The way you specify the invocation options depends on the environment in which High Level Assembler is running.

#### z/OS

In z/OS batch, you select the options by specifying them on the PARM field of the JCL EXEC statement that invokes the assembler. For example:

```
//ASSEMBLE EXEC PGM=ASMA90,PARM='LIST(133),DBCS'
```

You can also use catalogued procedures to invoke the assembler. To override options in a cataloged procedure, you must include the PARM field in the EXEC statement that invokes the procedure. If the cataloged procedure contains more than one step, you must also qualify the keyword parameter (PARM) with the name of the step within the procedure that invokes the assembler. For example:

```
// EXEC ASMACG,PARM.C='LIST(133),DBCS'
```

For more examples on how to specify options in a cataloged procedure, see “Overriding statements in cataloged procedures” on page 190.

On TSO, you select the options by specifying them in the second parameter of the TSO CALL command that invokes the assembler. For example:

```
CALL 'SYS1.LINKLIB(ASMA90)' 'LIST(133),DBCS'
```

End of z/OS

z/VM

You select the options by specifying them after the left parenthesis on the CMS ASMAHL command that invokes the assembler. For example:

```
ASMAHL filename (LIST(133) DBCS[])
```

End of z/VM

z/VSE

In batch, you select the options by specifying them in the PARM field of the EXEC JCL statement that invokes the assembler. You can also specify some of the options on the JCL OPTION statement. For example:

```
// OPTION TERM
// EXEC ASMA90,SIZE=ASMA90,PARM='LIST,DBCS'
```

**z/VSE ICCF:** On ICCF, you select the options by specifying them in the PARM field of the job entry statement /LOAD that invokes the assembler. For example:

```
/LOAD ASMA90
PARM='LIST,DBCS'
```

End of z/VSE

## \*PROCESS statement options

Process (\*PROCESS) statements let you specify assembler options in your assembler source program. You can include them in the primary input data set or provide them from a SOURCE user exit.

If you add the OVERRIDE keyword, then the option has a higher precedence than values set as default and invocation options (see “\*PROCESS OVERRIDE Statement Options” on page 40).

Some options cannot be set by a process statement. These are:

ADATA	LANGUAGE	PRINT (CMS)
ASA (z/OS and CMS)	LINECOUNT	SIZE
DECK	LIST	SYPARM
DISK (CMS)	MACHINE	TERM
EXIT	NOPRINT (CMS)	TRANSLATE
GOFF (z/OS and CMS)	OBJECT	XOBJECT (z/OS and CMS)

If you specify one of these options on a normal process statement, the assembler issues a warning message.

## Precedence of assembler options

Refer to “\*PROCESS statement” in the *HLASM Language Reference* for a description of the \*PROCESS statement.

## Default options

When High Level Assembler is installed, each assembler option is preset to a default. The IBM-supplied default options are shown above the main path of the syntax diagrams in the description of the assembler options that follow. However, these might *not* be the default options in effect at your installation; the defaults could have been changed when High Level Assembler was installed. For example, NOADATA is an IBM-supplied default, and ADATA might be the default at your installation. During an assembly you cannot override default options that were fixed during installation (see “Fixed installation default options” on page 40). The assembler issues a message if you try to override a fixed option.

**PESTOP:** If the PESTOP option was specified during installation, and an error is detected in the options you specify at run time, the assembly stops.

## Invoking the assembler dynamically

Assembler options can be passed in a parameter list when the assembler is invoked dynamically from an executing program. For further information, refer to “Invoking the assembler dynamically” on page 164 (for the z/OS platform) or “Invoking the assembler dynamically” on page 222 (for the z/VSE platform).

## Coding rules

The rules for coding the assembler options are:

- You can specify the options in any order.
- If you specify an incorrect option the assembler issues a diagnostic message, and sets the return code to 2 or higher. You can prevent the setting of the return code by using the FLAG option.

### z/VM

- If you specify two or more options, the options can be separated by spaces or commas.

End of z/VM

### z/OS

- If you specify two or more options, the list of options must be enclosed within single quotation marks or parentheses. Each option must be separated by a comma.
- If you specify only one option and it does not include any special characters, the enclosing single quotation marks or parentheses can be omitted.
- All options that have suboptions must be within single quotation marks because they contain special characters.
- If you need to continue the PARM field onto another record, the entire PARM field must be enclosed in parentheses. However, any part of the PARM field enclosed in single quotation marks must not be continued on another record.

End of z/OS

z/VSE

- You must enclose the options in single quotation marks and separate each option with a comma.
- If you need to continue the PARM field onto another record, place any character in column 72 of the record you wish to continue, and continue in column 16 on the following record.
- The operating system passes to the assembler any spaces you code in the PARM=JCL parameter, including those implied in a continuation. For example:  

```
// EXEC ASMA90,SIZE=(ASMA90,50K),PARM='RENT,SIZE(MAX-500K),EXIT(LIBEXIT/
(EDECKXIT))'
```

is not equivalent to:

```
// EXEC ASMA90,SIZE=(ASMA90,50K),PARM='RENT,SIZE(MAX-500K),
EXIT(LIBEXIT(EDECKXIT))'
```

The second example results in this diagnostic message:

```
** ASMA400W ERROR IN INVOCATION PARAMETER - EXIT (LIBEXIT(EDECKXIT))
```

End of z/VSE


Additional rules for coding the assembler options in the external file or library member are:

- Trailing spaces are ignored.
- If two or more options are specified in a record they must be separated by a comma.
- Only a SYSPARM options enclosed in quotes may be continued on another record.
- If a SYSPARM options contains embedded spaces it must be enclosed in quotes.
- The maximum length of the options list including the delimiting commas inserted by the assembler is 32766.

## Assembler options

Here are descriptions of the assembler options. The IBM-supplied default value for each option is shown above the main path in the syntax diagram. Your installation may have a different default (see “Default options” on page 42). There are minor variations for Linux on zSeries. See “Assembler options” on page 433 for details.

### ADATA



Default

NOADATA

## ADATA

### Abbreviations

None

### Restrictions

You cannot specify this option on \*PROCESS statements.

### ADATA

Specifies that the assembler collect associated data and write it to the associated data file. You define the associated data file with the SYSADATA ddname on z/OS and CMS, or with the SYSADAT filename on z/VSE.

Appendix D, “Associated data file output,” on page 267 describes the format of the associated data file.

### NOADATA

Specifies that the assembler is not to collect associated data. If you specify NOADATA, then the assembler ignores the EXIT(ADEXIT) option.

## ALIGN



### Default

ALIGN

### Abbreviations

None

### ALIGN

Instructs the assembler to check alignment of addresses in machine instructions for consistency with the requirements of the operation code type. DC, DS, DXD, and CXD are to be aligned on the correct boundaries.

### NOALIGN


Instructs the assembler not to check alignment of machine instruction data references not always requiring operand alignment, but still to check instruction references and machine instruction data references always requiring operand alignment. DC, DS, and DXD are to be aligned on the correct boundaries only if the duplication factor is 0.

### Notes:

1. Specify the FLAG(NOALIGN) option to suppress the message issued when the assembler detects an alignment inconsistency.
2. If your program is assembled with data areas or DSECT for interfacing with IBM products, you should use the default (ALIGN) unless specifically directed otherwise.
3. On z/VSE, you can specify the ALIGN option on the JCL OPTION statement.



## ASA (z/OS and CMS)



### Default

NOASA

### Abbreviations

None

### Restrictions

You cannot specify this option on \*PROCESS statements.


### ASA

Instructs the assembler to use American National Standard printer control characters in records written to the listing data set.

### NOASA

Instructs the assembler to use machine printer control characters in records written to the listing data set.

## BATCH



### Default

BATCH

### Abbreviations

None


### BATCH

Instructs the assembler that multiple assembler source programs may be in the input data set. The first statement of the second and subsequent source programs must immediately follow the assembled END statement of the previous source program. An end-of-file must immediately follow the last source program.

### NOBATCH

Instructs the assembler that only one assembler source program is in the input data set.

## CODEPAGE

**Default**

CODEPAGE(1148|X'47C')

**Abbreviation**

CP

**1148|X'47C'**

Specifies that characters contained in the Unicode character (CU-type) data constants (DCs) are to be converted using the ECECP: International 1 Unicode-3 mappings contained in module ASMA047C.

**nnnnn|X'xxxx'**


Specifies that characters contained in the Unicode character (CU-type) data constants (DCs) are to be converted using the Unicode mapping table module ASMAxxxx where xxxx is the hexadecimal value of the number nnnnn which is the number of the code page contained in the module. The number must be in the range 1 through 64k-1.

The following Unicode-3 code pages are supported by the assembler:

Table 7. Unicode-3 SBCS mapping code pages

Code Page	Module Name	Description
1140	ASMA0474	ECECP: USA, Canada, Netherlands, Portugal, Brazil, Australia, New Zealand
1141	ASMA0475	ECECP: Austria, Germany
1142	ASMA0476	ECECP: Denmark, Norway
1143	ASMA0477	ECECP: Finland, Sweden
1144	ASMA0478	ECECP: Italy
1145	ASMA0479	ECECP: Spain, Latin America (Spanish)
1146	ASMA047A	ECECP: United Kingdom
1147	ASMA047B	ECECP: France
1148	ASMA047C	ECECP: International 1

## COMPAT



### Default

NOCOMPAT

### Abbreviations

CPAT(CASE, NOCASE, LIT, NOLIT, MC, NOMC, SYSL, NOSYSL) / NOCPAT

### Parameter of ACONTROL statement

You can specify the COMPAT (or NOCOMPAT) option as a parameter of the ACONTROL statement. For further details, refer to the “ACONTROL instruction” in the *HLASM Language Reference*.

### CASE

Instructs the assembler to maintain uppercase alphabetic character set compatibility with earlier assemblers. It restricts language elements to uppercase alphabetic characters A through Z if they were so restricted in earlier assemblers.

### NOCASE

Instructs the assembler to allow a mixed-case alphabetic character set.

### LITTYPE

Instructs the assembler to return “U” as the type attribute for all literals.

### NOLITTYPE

Instructs the assembler to provide the correct type attribute for literals once they have been defined.

### MACROCASE

Instructs the assembler to convert (internally) lowercase alphabetic characters (*a* through *z*) in unquoted macro operands to uppercase alphabetic characters (*A* through *Z*).

### NOMACROCASE

Instructs the assembler not to convert (internally) lowercase alphabetic characters (*a* through *z*) in unquoted macro operands.

## COMPAT

### SYSLIST

Instructs the assembler to treat sublists in SETC symbols as compatible with earlier assemblers. SETC symbols that are assigned parenthesized sublists are treated as character strings, not sublists, when passed to a macro definition in an operand of a macro instruction.


### NOSYSLIST

Instructs the assembler not to treat sublists in SETC symbols as character strings, when passed to a macro definition in an operand of a macro instruction.

### NOCOMPAT

Instructs the assembler to allow lowercase alphabetic characters *a* through *z* in all language elements, to treat sublists in SETC symbols as sublists when passed to a macro definition in the operand of a macro instruction, and to provide the correct type attribute for literals once they have been defined.

## DBCS



### Default

NODBCS

### Abbreviations

None


### DBCS

Instructs the assembler to accept double-byte character set data, and to support graphic (G-type) constants and self-defining terms. The assembler recognizes X'0E' and X'0F' in character strings enclosed by single quotation marks, and treats them as Shift-Out and Shift-In control characters for delimiting DBCS data.

### NODBCS

Specifies that the assembler does not recognize X'0E' and X'0F' as double-byte character set data delimiters, and does not support graphic (G-type) constants and self-defining terms.

## DECK



### Default

NODECK

### Abbreviations

None

**Restrictions**

You cannot specify this option on \*PROCESS statements.

**DECK**

Specifies that the assembler generate object code and write it to the object data set. You define the object data set with the SYSPUNCH ddname on z/OS and CMS, or with the IJSYSPH filename and by assigning SYSPCH on z/VSE.

**NODECK**


Instructs the assembler not to write the object code to SYSPUNCH on z/OS and CMS, or SYSPCH on z/VSE.

If you specify NODECK and NOOBJECT, the assembler ignores the EXIT(OBJEXIT)) option.

On z/VSE, you can only specify the DECK option on the JCL OPTION statement. If you specify it on the PARM operand of the JCL EXEC statement, the assembler issues message ASMA400W, and ignores the option.

**DISK (CMS)**

See “PRINT (CMS)” on page 69.

**DXREF****Default**

DXREF

**Abbreviations**

DX / NODX


**DXREF**

Instructs the assembler to produce the DSECT Cross Reference section of the assembler listing. The DSECT cross reference includes:

- The symbolic names of all DSECTs defined in the assembly
- The assembled length of each DSECT
- The ESDID of each DSECT
- The statement number which defines the DSECT

**NODXREF**

Instructs the assembler not to produce the DSECT Cross Reference section of the assembler listing.

**ERASE (CMS)**

## ERASE

### Default

ERASE

### Abbreviations

None

### Restrictions

This option is not allowed on \*PROCESS statements.

This option can only be specified when you use the ASMAHL command on CMS.

### ERASE

Specifies that the existing files with a filename the same as the filename on the ASMAHL command, and a filetype of LISTING, TEXT, and SYSADATA, are to be deleted before the assembly is run. Only files on the disk on which the assembler writes the new listing, object, and associated data files are deleted.

### NOERASE

Specifies that the existing LISTING, TEXT, and SYSADATA files are not to be deleted before the assembly is run.

## ESD



### Default

ESD

### Abbreviations

None

### ESD


Instructs the assembler to produce the External Symbol Dictionary section of the assembler listing. The ESD contains the external symbol dictionary information that is passed to the linkage editor or loader, or z/OS binder, in the object module.

### NOESD

Instructs the assembler not to produce the External Symbol Dictionary section of the assembler listing.

On z/VSE, you can specify this option on the JCL OPTION statement.

## EXIT

**Default**

NOEXIT

**Abbreviations**

EX(INX, NOINX, LBX, NOLBX, PRX, NOPRX, OBX, NOOBX, ADX, NOADX, TRX, NOTRX) / NOEX

**Restrictions**

You cannot specify this option on \*PROCESS statements.

**INEXIT**

Specifies that the assembler use an input (SOURCE) exit for the assembly. *mod1* is the name of the load module for the exit. The assembler passes control to the load module for SOURCE type exit processing, and provides a pointer to *str1* in a parameter list when the exit is first called. For a full description, see Chapter 4, “Providing user exits,” on page 87.

You can use a SOURCE exit, for example, to read variable-length source input records. See also Appendix K, “Sample SOURCE user exit (z/OS and CMS),” on page 405.

**NOINEXIT**

Specifies that there is no SOURCE exit.

## EXIT

### LIBEXIT

Specifies that the assembler use a LIBRARY exit for the assembly. *mod2* is the name of the load module for the exit. The assembler passes control to the load module for LIBRARY type exit processing, and provides a pointer to *str2* in a parameter list when the exit is first called. For a full description, see Chapter 4, “Providing user exits,” on page 87.

On CMS, you can use this exit, for example, to handle non-standard libraries, or macros and copy books that are in separate CMS files instead of CMS MACLIBs.

On z/VSE, you can use this exit to handle edited macros from the library sublibraries.

Refer to *VSE/ESA Guide to System Functions* for a description of a LIBRARY exit to read edited macros.

### NOLIBEXIT

Specifies that there is no LIBRARY exit.

### PRTEXTIT

Specifies that the assembler use a LISTING exit for the assembly. *mod3* is the name of the load module for the exit. The assembler passes control to the load module for LISTING type exit processing, and provides a pointer to *str3* in a parameter list when the exit is first called. For a full description, see Chapter 4, “Providing user exits,” on page 87.

You can use the LISTING exit, for example, to suppress parts of the assembly listing, or provide additional listing lines. See also Appendix J, “Sample LISTING user exit (z/OS and CMS),” on page 403.

### NOPRTEXTIT

Specifies that there is no LISTING exit.

### OBJEXIT

On z/OS and CMS, specifies that the assembler use an OBJECT exit or PUNCH exit, or both, for the assembly. *mod4* is the name of the load module for the exit. The assembler passes control to the load module for OBJECT type exit processing when you specify either the OBJECT or GOFF option, and provides a pointer to *str4* in a parameter list when the exit is first called. For a full description, see Chapter 4, “Providing user exits,” on page 87. The assembler passes control to the load module for PUNCH type exit processing when you specify the DECK option. The OBJEXIT suboption is ignored if you specify the assembler options NODECK and NOOBJECT.

On z/VSE, specifies that the assembler use a PUNCH exit for the assembly. The name of the load module for the exit is *mod4*. The assembler passes control to the load module for PUNCH type exit processing when you specify the DECK option. You can use the PUNCH exit, for example, to catalog object modules directly into a library sublibrary.

### NOOBJEXIT

Specifies that there is no OBJECT exit or PUNCH exit.

### ADEXIT

Specifies that the assembler use an ADATA exit for the assembly. *mod5* is the name of the load module for the exit. The assembler passes control to the load module for ADATA type exit processing, and provides a pointer to *str5* in a parameter list when the exit is first called. For a full description, see Chapter 4, “Providing user exits,” on page 87. See also Appendix I, “Sample ADATA user exits (z/OS and CMS),” on page 391.



**NOADEXIT**

Specifies that there is no ADATA exit.

**TRMEXIT**

Specifies that the assembler use a TERM exit for the assembly. *mod6* is the name of the load module for the exit. The assembler passes control to the load module for TERM type exit processing, and provides a pointer to *str6* in a parameter list when the exit is first called. For a full description, see Chapter 4, “Providing user exits,” on page 87.

**NOTRMEXIT**

Specifies that there is no TERM exit.

**NOEXIT**

Specifies that there are no exits for the assembly.


The module names *mod1*, *mod2*, *mod3*, *mod4*, *mod5*, and *mod6* can refer to the same load module.

The suboptions *str1*, *str2*, *str3*, *str4*, *str5*, and *str6* are optional. They are character strings, up to 64 characters in length, that are passed to the exit module during OPEN processing. You may include any character in a string, but you must pair parentheses. JCL restrictions require that you specify two single quotation marks to represent a single quotation mark, and two ampersands to represent a single ampersand.

For more information about the EXIT option, see Chapter 4, “Providing user exits,” on page 87.

You specify these options in the installation default options using the ADEXIT, INEXIT, LIBEXIT, OBJEXIT, PRTEXTIT, and TRMEXIT operands.

## FLAG



### Default

FLAG(0, ALIGN, CONT, NOIMPLEN, NOPAGE0, PUSH, RECORD, NOSUBSTR, USING0, EXLITW)

### Abbreviations

AL, NOAL, IMP, NOIMP, PG0, NOPG0, PU, NOPU, RC, NORC, SUB, NOSUB, US0, NOUS0

### Parameter of ACONTROL statement

You can specify the FLAG option as a parameter of the ACONTROL statement. For further details, refer to the “ACONTROL instruction” in the *HLASM Language Reference*.

### integer

Specifies that error diagnostic messages with this or a higher severity code are printed in the *source and object* section of the assembly listing. Error diagnostic messages with a severity code lower than *integer* do not appear in the *source and object* section, and the severity code associated with those messages is not used to set the return code issued by the assembler. Any severity code from 0

through 255 may be specified. Error diagnostic messages have a severity code of 0, 2, 4, 8, 12, 16, or 20. MNOTEs can have a severity code of 0 through 255.

When specified with the TERM assembler option, FLAG controls which messages are displayed in the terminal output.

### **ALIGN**

Instructs the assembler to issue diagnostic message ASMA033I when an inconsistency is detected between the operation code type and the alignment of addresses in machine instructions. Assembler option ALIGN describes when the assembler detects an inconsistency.

### **NOALIGN**

Instructs the assembler not to issue diagnostic messages ASMA033I, ASMA212W and ASMA213W when an inconsistency is detected between the operation code type and the alignment of addresses in machine instructions.

### **CONT**

Specifies that the assembler is to issue diagnostic messages ASMA430W through ASMA433W when one of the following situations occurs in a macro call instruction:

- The operand on the continued record ends with a comma, and a continuation statement is present but continuation does not start in the continue column (usually column 16).
- A list of one or more operands ends with a comma, but the continuation indicator field (usually column 72) is a space.
- The continuation record starts in the continue column (usually column 16) but there is no comma present following the operands on the previous record.
- The continued record is full but the continuation record does not start in the continue column (usually column 16).

**Note:** FLAG(CONT) checks only apply to statements that appear in the output listing.

### **NOCONT**

Specifies that the assembler is not to issue diagnostic messages ASMA430W through ASMA433W when an inconsistent continuation is encountered.

### **IMPLEN**

Instructs the assembler to issue diagnostic message ASMA169I when an explicit length subfield is omitted from an SS-format machine instruction.

### **NOIMPLEN**

Instructs the assembler not to issue diagnostic message ASMA169I when an explicit length subfield is omitted from an SS-format machine instruction.

### **PAGE0**

Instructs the assembler to issue diagnostic message ASMA309W when an operand is resolved to a baseless address and a base and displacement is expected. This message is only issued for instructions that reference storage. For example, a LOAD instruction generates the message but a LOAD ADDRESS instruction does not generate the message.

### **NOPAGE0**

Instructs the assembler not to issue diagnostic message ASMA309W when an operand is resolved to a baseless address and a base and displacement is expected.

## FLAG

The FLAG suboptions PAGE0 and IMLEN are specified in the installation default options as PAGE0WARN and IMLENWARN respectively.

### PUSH

Instructs the assembler to issue diagnostic warning message ASMA138W when a PUSH/POP stack is not empty at the completion of a compile.

### NOPUSH

Instructs the assembler to suppress diagnostic warning message ASMA138W when a PUSH/POP stack is not empty at the completion of a compile.

### RECORD

Instructs the assembler to do the following:

- Issue diagnostic message ASMA435I immediately after the last diagnostic message for each statement in error. The message text describes the record number and input data set name of the statement in error.
- Include the member name (if applicable), the record number and the input data set concatenation value with the statement number in the list of flagged statements in the Diagnostic Cross Reference and Assembler Summary section of the assembler listing.

### NORECORD

Instructs the assembler to do the following:

- Not issue diagnostic message ASMA435I for statements in error.
- Only show the statement number in the list of flagged statements in the Diagnostic Cross Reference and Assembler Summary section of the assembler listing.

### SUBSTR

Instructs the assembler to issue warning diagnostic message ASMA094I when the second subscript value of the substring notation indexes past the end of the character expression.

### NOSUBSTR

Instructs the assembler not to issue warning diagnostic message ASMA094I when the second subscript value of the substring notation indexes past the end of the character expression.

### USING0

Instructs the assembler to issue diagnostic warning message ASMA306W for a USING that is coincident with or overlaps an implied USING 0,0, when the USING(WARN) suboption includes the condition numbers 1 and/or 4.

**Note:** Message ASMA302W is issued when R0 is specified as a base register with a non-zero base address, and message ASMA306W is issued when any register other than R0 is specified as a base register with an absolute base address whose range overlaps the assembler's default (0,4095).

### NOUSING0

Instructs the assembler to suppress diagnostic warning message ASMA306W.

**Note:** Message ASMA302W is issued when R0 is specified as a base register with a non-zero base address, and message ASMA306W is issued when any register other than R0 is specified as a base register with an absolute base address whose range overlaps the assembler's default (0,4095).

### EXLITW


Instructs the assembler to issue diagnostic warning ASMA016W when a literal is used as the object of an EX instruction.

**NOEXLITW**

Instructs the assembler to suppress diagnostic warning message ASMA016W when a literal is used as the object of an EX instruction.

The FLAG suboptions ALIGN, CONT, IMPLEN, PAGE0, PUSH, RECORD, SUBSTR, USING0, and EXLITW are specified in the installation default options as ALIGNWARN, CONTWARN, IMPLENWARN, PAGE0WARN, PUSHWARN, RECORDINFO, SUBSTRWARN, USING0WARN, and EXLITW respectively.

For information about installation default options, please refer to the *HLASM Installation and Customization Guide*.

**FOLD****Default**

NOFOLD

**Abbreviations**


None

**FOLD**

Instructs the assembler to convert lowercase alphabetic characters (a through z) in the assembly listing to uppercase alphabetic characters (A through Z). All lowercase alphabetic characters are converted, including lowercase characters in source statements, listing headings, assembler error diagnostic messages, and assembly listing lines provided by a user exit. Lowercase alphabetic characters are converted to uppercase alphabetic characters, regardless of the setting of the COMPAT(CASE) option. If the LANGUAGE option specifies a language other than English, it is possible that headings are not converted to upper case.

**NOFOLD**

Specifies that lowercase alphabetic characters are not converted to uppercase alphabetic characters.

**GOFF (z/OS and CMS)****Default**

NOGOFF

### Abbreviations

None

### Restrictions

You cannot specify this option on \*PROCESS statements.

### GOFF

Instructs the assembler to produce a Generalized Object File format (GOFF) data set. You define this data set with the SYSLIN or SYSPUNCH ddname.

**Note:** For more information on the GOFF format, refer to *z/OS DFSMS Program Management*.

### NOADATA

The same as GOFF without a suboption.

### ADATA

Instructs the assembler to produce a Generalized Object File format data set, and include ADATA text records.

### NOGOFF

Instructs the assembler not to produce a Generalized Object File format data set.

### Notes:

1. You should specify the LIST(133) option when you specify the GOFF option. If the logical record length of the listing data set is less than 133, the assembler truncates the listing lines.
2. The generalized object format does not support TEST (SYM) records. If you specify the TEST option with the GOFF option, the assembler issues a diagnostic error message.
3. The assembler option XOBJECT is treated as a synonym for the GOFF option and accepts the same subparameters as GOFF.

For more information on the 133-character format, see “Source and object” on page 14.

When the GOFF option is not specified a control section is initiated or resumed by the CSECT, RSECT, and COM statements. Any machine language text created by statements that follow such control section declarations belongs to the control section, and is manipulated during program linking and binding as an indivisible unit.


When the GOFF option is specified, the behavior of statements like CSECT is somewhat different. By default, the assembler creates a definition of a text class named B\_TEXT, to which subsequent machine language text belongs if no other classes are declared. If you specify other class names using the CATTR statement, machine language text following such CATTR statements belongs to that class.

The combination of a section name and a class name defines an *element*, which is the indivisible unit manipulated during linking and binding. All elements with the same section name are “owned” by that section, and binding actions (such as section replacement) act on all elements owned by a section.

When the GOFF option is specified, and if no CATTR statements are present, then all machine language text is placed in the default class B\_TEXT, and the behavior of the elements in the bound module is essentially the same as the behavior of control sections when the OBJECT option is specified. However, if additional

classes are declared, a section name can best be thought of as a "handle" by which elements within declared classes are owned.

INFO



Default

NOINFO

Abbreviations

None

INFO

Instructs the assembler to copy to the list data set all product information.

The Product Information Page (see Figure 21) follows the Option Summary,

INFO(yyyymmdd)

Instructs the assembler not to copy to the list data set any product information which is dated prior to *yyymmdd*.

NOINFO

Instructs the assembler not to copy any product information to the list data set.





Figure 21. High Level Assembler product information page

(This page from a previous release of HLASM, for illustrative purposes only.)

## LANGUAGE



### Default

LANGUAGE(EN)

### Abbreviations

LANG(EN | ES | DE | JP | UE)

### Restrictions

This option is not allowed on \*PROCESS statements.

### EN

Specifies that the assembler issues messages, and prints the assembler listing headings in mixed uppercase and lowercase English.

### DE

Specifies that the assembler issues messages in German. The assembler listing headings are printed in mixed-case English.

### ES

Specifies that the assembler issues messages in Spanish. The assembler listing headings are printed in mixed-case English.

### JP


Specifies that the assembler issues messages in Japanese. The assembler listing headings are printed in uppercase English.

### UE

Specifies that the assembler issues messages, and prints the assembler listing headings in uppercase English.

**Note:** The assembler uses the language specified in the installation default options for messages produced in CMS by the ASMAHL command.

## LIBMAC



### Default

NOLIBMAC

### Abbreviations

LMAC / NOLMAC

### Parameter of ACONTROL statement

You can specify the LIBMAC (or NOLIBMAC) option as a parameter of the



ACONTROL statement. For further details, refer to the “ACONTROL instruction” in the *HLASM Language Reference*.


### LIBMAC

Specifies that, for each macro, macro definition statements read from a macro library are to be embedded in the input source program immediately preceding the first invocation of that macro. The assembler assigns statement numbers to the macro definition statements as though they were included in the input source program.

### NOLIBMAC

Specifies that macro definition statements read from a macro library are not included in the input source program.

## LINECOUNT



### Default

LINECOUNT(60)

### Abbreviations

LC(*integer*)

*CMS Only:*

The LINECOUNT option can be abbreviated to LINECOUN.

### Restrictions

This option is not allowed on \*PROCESS statements.


### LINECOUNT(*integer*)

Specifies the number of lines to be printed on each page of the assembly listing. *integer* must have a value of 0, or 10 to 32767.

If a value of 0 is specified, no page ejects are generated and EJECT, CEJECT, and TITLE statements in the assembly are ignored; there is only one eject character in the listing and that is at the top of the listing at the first line. From there on there are no headings, no ejects, and no titles. No eject characters are inserted at the start of sections of the listing (such as the ESD and RLD).

Up to 7 lines on each page may be used for heading lines.

## LIST



## LIST

### Default

LIST(121)

### Abbreviations

None

### Restrictions

You cannot specify this option on \*PROCESS statements.

### LIST

Instructs the assembler to produce a listing. Specifying LIST without a suboption is equivalent to specifying LIST(121).

### 121 (z/OS and CMS)

Instructs the assembler to produce a listing, and print the Source and Object section in the 121-character format.

### 133 (z/OS and CMS)

Instructs the assembler to produce a listing, and print the Source and Object section in the 133-character format. You should use this option when you specify the GOFF option.

### MAX (z/OS and CMS)


Instructs the assembler to produce a listing, and print the Source and Object section in either the 121-character format or the 133-character format. If the logical record length (LRECL) of the listing data set is less than 133 then the assembler selects the 121-character format. If the LRECL of the listing data set is 133 or more then the assembler selects the 133-character format.

### NOLIST

Instructs the assembler to suppress the assembly listing. When you specify NOLIST the assembler ignores the following options:

DXREF	PCONTROL
ESD	RLD
EXIT(PRTEXTIT)	RXREF
INFO	USING(MAP)
MXREF(MAP)	XREF

## MACHINE



### Abbreviations

MAC

## Restrictions

None

### S370

Instructs the assembler to load and use the operation code table that contains the System/370 machine instructions, including those with a vector facility. Equivalent to OPTABLE(370).

### S370XA

Instructs the assembler to load and use the operation code table that contains the System/370 extended architecture machine instructions, including those with a vector facility. Equivalent to OPTABLE(XA).

### S370ESA

Synonym for MACHINE(S390E).

### S390

Synonym for MACHINE(S390E).

### S390E

Instructs the assembler to load and use the operation code table that contains the ESA/370 and ESA/390 architecture machine instructions, including those with a vector facility. Equivalent to OPTABLE(ESA).

### ZSERIES

Instructs the assembler to load and use the operation code table that contains the symbolic operation codes for the machine instructions specific to z/Architecture systems. Equivalent to OPTABLE(ZOP).

### ZS

Synonym for MACHINE(ZSERIES).

### ZSERIES-2

Same as MACHINE(ZSERIES) but with the addition of the long displacement facility. Equivalent to OPTABLE(YOP).

### ZS-2

Synonym for MACHINE(ZSERIES-2).

### ZSERIES-3

Same as MACHINE(ZSERIES-2) but with the addition of support for the z9-109 instructions. Equivalent to OPTABLE(ZS3).

### ZS-3

Synonym for MACHINE(ZSERIES-3).

### ZSERIES-4

Same as MACHINE(ZSERIES-3) but with the addition of support for the z10 instructions. Equivalent to OPTABLE(ZS4).

### ZS-4

Synonym for MACHINE(ZSERIES-4).

### LIST

Instructs the assembler to produce the Operation Code Table Contents section in the listing. Equivalent to OPTABLE(LIST).

### NOLIST

Instructs the assembler not to produce the Operation Code Table Contents section in the listing. Equivalent to OPTABLE(NOLIST).

### Notes:

1. The operation codes supported by High Level Assembler are described in the documents listed under "Related Publications (Architecture)" on page 451.


## MACHINE

2. Table 8 shows the equivalent sub-options for the MACHINE and OPTABLE options.

*Table 8. Equivalent sub-options for MACHINE and OPTABLE options*

MACHINE sub-option	OPTABLE sub-option	Output in assembler listing
	UNI	MACHINE(,NOLIST)
	DOS	MACHINE(,NOLIST)
S370	370	MACHINE(S370,NOLIST)
S370XA	XA	MACHINE(S370XA,NOLIST)
S370ESA	ESA	MACHINE(S390,NOLIST)
S390	ESA	MACHINE(S390,NOLIST)
S390E	ESA	MACHINE(S390,NOLIST)
ZSERIES	ZOP	MACHINE(ZSERIES,NOLIST)
ZS	ZOP	MACHINE(ZSERIES,NOLIST)
ZSERIES-2	YOP	MACHINE(ZSERIES-2,NOLIST)
ZS-2	YOP	MACHINE(ZSERIES-2,NOLIST)
ZSERIES-3	ZS3	MACHINE(ZSERIES-3,NOLIST)
ZS-3	ZS3	MACHINE(ZSERIES-3,NOLIST)
ZSERIES-4	ZS4	MACHINE(ZSERIES-4,NOLIST)
ZS-4	ZS4	MACHINE(ZSERIES-4,NOLIST)

## MXREF



### Default

MXREF(SOURCE)

### Abbreviations

MX / NOMX

### MXREF

Specifying MXREF without a suboption is equivalent to specifying MXREF(SOURCE).

### SOURCE

Instructs the assembler to produce the Macro and Copy Code Source Summary section of the assembler listing. The macro and copy code source summary includes the name of each macro library or copy library accessed, the volume serial number of the first DASD volume on which the library resides, and the names of each member retrieved from the library.

**FULL**

Instructs the assembler to produce the Macro and Copy Code Source Summary section and the Macro and Copy Code Cross Reference section of the assembler listing.

**Note:** See note following MXREF(XREF).


**XREF**

Instructs the assembler to produce the Macro and Copy Code Cross Reference section of the assembler listing. The Macro and Copy Code Cross Reference includes the name of each macro or copy code member referenced in the assembly, where it was referenced and where it was called or copied from.

**Note:** If you specify MXREF(FULL) or MXREF(XREF), you might need to review the value of the SIZE option (as both of these assembler options use considerable amounts of storage).

**NOMXREF**

Specifies that macro and copy code information is not generated in the assembler listing.

**OBJECT****Default**

OBJECT

**Abbreviations**

OBJ / NOOBJ

**Restrictions**

You cannot specify this option on \*PROCESS statements.

**OBJECT**


Instructs the assembler to generate object code and write it to the object data set. You define the object data set with the SYSLIN ddname, on z/OS and CMS, or with the IJSYSLN filename and by assigning SYSLNK on z/VSE.

**NOOBJECT**

Instructs the assembler not to write the object code to SYSLIN, on z/OS and CMS, or SYSLNK on z/VSE.

On z/VSE, you can only specify the OBJECT option by using the LINK or CATAL option on the JCL OPTION statement. If you specify OBJECT on the PARM operand of the JCL EXEC statement, the assembler issues message ASMA400W, and ignores the option.

## OPTABLE



### Default

OPTABLE(UNI,NOLIST)

### Abbreviation

OP

### Restrictions

None

### DOS

Instructs the assembler to load and use the DOS operation code table. The DOS operation code is designed specifically for assembling programs previously assembled using the DOS/VSE assembler. The operation code table contains the System/370 machine instructions, excluding those with a vector facility.

### ESA

Instructs the assembler to load and use the operation code table that contains the ESA/370 and ESA/390 architecture machine instructions, including those with a vector facility. Equivalent to MACHINE(S390E).

### UNI

Instructs the assembler to load and use the operation code table that contains the System/370 and System/390 architecture machine instructions, including those with a vector facility, and Z/Architecture machine instructions.

### XA

Instructs the assembler to load and use the operation code table that contains the System/370 extended architecture machine instructions, including those with a vector facility. Equivalent to MACHINE(S370XA).

### 370

Instructs the assembler to load and use the operation code table that contains the System/370 machine instructions, including those with a vector facility. Equivalent to MACHINE(S370).

### YOP

Same as OPTABLE(ZOP) but with the addition of the long displacement facility. Equivalent to MACHINE(ZSERIES-4).

### ZOP

Instructs the assembler to load and use the operation code table that contains the symbolic operation codes for the machine instructions specific to Z/Architecture systems. Equivalent to MACHINE(ZSERIES).

**ZS3**  
Instructs the assembler to load and use the operation code table that contains the symbolic operation codes for the machine instructions specific to Z/Architecture systems. Equivalent to MACHINE(ZSERIES).


**ZS4**  
Instructs the assembler to load and use the operation code table that contains the symbolic operation codes for the machine instructions specific to Z/Architecture systems. Equivalent to MACHINE(ZSERIES).

**LIST**  
Instructs the assembler to produce the Operation Code Table Contents section in the listing. Equivalent to MACHINE(LIST).

**NOLIST**  
Instructs the assembler not to produce the Operation Code Table Contents section in the listing. Equivalent to MACHINE(NOLIST).

- Notes:**
- 1. These operation code tables do not contain symbolic operation codes for machine instructions that are unique to IBM 4300 Processors operating in ECPS:VSE mode.
  - 2. The operation codes supported by High Level Assembler are described in the documents listed under “Related Publications (Architecture)” on page 451.
  - 3. Table 8 on page 64 shows the equivalent sub-options for the OPTABLE and MACHINE options.

PCONTROL



## PCONTROL

### Default

NOPCONTROL

### Abbreviations

PC(DATA, NODATA, GEN, NOGEN, MC, NOMC, MS, NOMS, ON, OFF, UHD, NOUHD) / NOPC

### DATA

Specifies that the assembler is to print the object code of all constants in full, as though a PRINT DATA statement were specified at the beginning of the source program. All PRINT NODATA statements in the source program are ignored. However, specifying PCONTROL(DATA) does not override PRINT OFF or PRINT NOGEN statements in the source program.

### NOADATA

Specifies that the assembler is to print only the first 8 bytes of the object code of constants, as though a PRINT NODATA statement were specified at the beginning of the source program. All PRINT DATA statements in the source program are ignored.

### GEN

Specifies that the assembler is to print all statements generated by the processing of a macro, as though a PRINT GEN statement were specified at the beginning of the source program. All PRINT NOGEN statements in the source program are ignored. However, specifying PCONTROL(GEN) does not override PRINT OFF statements in the source program.

### NOGEN

Specifies that the assembler is not to print statements generated by the processing of a macro or open code statements with substitution variables, as though a PRINT NOGEN statement were specified at the beginning of the source program. All PRINT GEN and PRINT MSOURCE statements in the source program are ignored.

### MCALL

Specifies that the assembler is to print nested macro instructions, as though a PRINT MCALL statement were specified at the beginning of the source program. All PRINT NOMCALL statements in the source program are ignored. However, specifying PCONTROL(MCALL) does not override PRINT OFF or PRINT NOGEN statements in the source program.

### NOMCALL

Instructs the assembler not to print nested macro instructions, as though a PRINT NOMCALL statement were specified at the beginning of the source program. All PRINT MCALL statements in the source program are ignored.

### MSOURCE

Specifies that the assembler is to print the source statements generated during conditional assembly substitution or macro processing, as well as the assembled addresses and generated object code of the statements. All PRINT NOMSOURCE statements in the source program are ignored. However, specifying PCONTROL(MSOURCE) does not override PRINT OFF or PRINT NOGEN statements in the source program. PRINT GEN statements or the PCONTROL(GEN) option must be active for this option to have effect.

### NOMSOURCE

Instructs the assembler to suppress the printing of source statements generated during conditional assembly substitution or macro processing, but not suppress the printing of the assembled addresses and generated object code of the



statements. All PRINT MSOURCE statements in the source program are ignored. PRINT GEN statements or the PCONTROL(GEN) option must be active for this option to have effect.

**OFF**

Specifies that the assembler is not to produce the Source and Object section of the assembly listing. All PRINT ON statements in the source program are ignored.

**ON**

Specifies that the assembler is to produce an assembly listing unless the NOLIST option is specified. All PRINT OFF statements in the source program are ignored.

**UHEAD**

Specifies that the assembler is to print a summary of active USINGs in the heading lines of each page of the source and object code section of the listing, as though a PRINT UHEAD statement were specified at the beginning of the source program. All PRINT NOUHEAD statements in the source program are ignored. However, specifying PCONTROL(UHEAD) does not override PRINT OFF statements in the source program.

**NOUHEAD**

Instructs the assembler not to print a summary of active USINGs, as though a PRINT NOUHEAD statement were specified at the beginning of the source program. All PRINT UHEAD statements in the source program are ignored.


**NOPCONTROL**

Specifies that the assembler honor all PRINT statements in the source program. The standard PRINT operands active at the beginning of an assembly are ON, GEN, NODATA, NOMCALL, MSOURCE, and UHEAD.

**NOLIST Assembler Option:** The PCONTROL option cannot be used to override the NOLIST option. If the NOLIST option is specified, the PCONTROL option is ignored.

**PESTOP**

PESTOP is an installation-default option that instructs the assembler to terminate when an error is detected in the invocation parameters or \*PROCESS statements. Refer to “PESTOP” in the *HLASM Installation and Customization Guide* for instructions how to specify this option.

**PRINT (CMS)****Default**

DISK

**Abbreviations**

PR / NOPR / DI

## PRINT

### Restrictions

This option is not allowed on \*PROCESS statements.

This option can only be specified when you use the ASMAHL command on CMS.

### PRINT

Specifies that the LISTING file is to be written on the virtual printer.


### NOPRINT

Specifies that the writing of the LISTING file is suppressed. Any diagnostic messages to be written to SYSTERM are not affected.

### DISK

Specifies that the LISTING file is to be written to disk.

## PROFILE



### Default

NOPROFILE

### Abbreviations

PROF / NOPROF

### PROFILE

Instructs the assembler to copy the installation-default profile member into the source program, as if the source program contained a COPY instruction.

The assembler generates a COPY instruction for the specified member after it has processed any ICTL and \*PROCESS instructions at the beginning of the program. Because this COPY instruction ends the scan for these special instructions, the profile cannot contain ICTL or \*PROCESS statements.

#### *name*

Instructs the assembler to copy the member *name* into the source program, as if the source program contained a COPY instruction (see “COPY instruction” in the *HLASM Language Reference*).

### NOPROFILE


Specifies that the assembler is not to copy a library member into the source program.

### Notes:

1. The profile member is copied into the source program immediately following an ICTL statement or the last \*PROCESS statement.
2. You specify the default profile member name in the PROFMEM parameter of the installation options macro ASMAOPT. If the PROFMEM parameter is not specified, ASMAOPT generates a default member name of ASMAPROF. Refer to “ASMAOPT” in the *HLASM Installation and Customization Guide* for instructions how to use the ASMAOPT macro.
3. On z/OS and CMS, the assembler searches for the member in the macro and copy code libraries defined in the SYSLIB DD statement.

4. On z/VSE, the assembler searches for the member in the macro and copy code libraries defined in the LIBDEF job control statement.
5. The assembler processes the source statements in the profile member the same way it does for source statements obtained using the COPY instruction. Refer to “COPY instruction” in the *HLASM Language Reference* for further information about the COPY instruction.

## RA2



### Default

NORA2

### Abbreviations

None

### Parameter of ACONTROL statement

You can specify the RA2 (or NORA2) option as a parameter of the ACONTROL statement. For further details, refer to “ACONTROL instruction” in the *HLASM Language Reference*.


### RA2

Instructs the assembler to suppress error diagnostic message ASMA066W when 2-byte relocatable address constants, such as AL2(\*) and Y(\*), are defined in the source program.

### NORA2

Instructs the assembler to issue error diagnostic message ASMA066W when 2-byte relocatable address constants, such as AL2(\*) and Y(\*), are defined in the source program.

## RENT



### Default

NORENT

### Abbreviations

None

### RENT

Specifies that the assembler checks for possible coding violations of program reenterability. Non-reenterable code is identified by an error message, but is


## RENT

not exhaustively checked because the assembler cannot check the logic of the code. Therefore, the assembler might not detect all violations of program reenterability.

## NORENT

Specifies that the assembler not check for possible coding violations of program reenterability.

## RLD



### Default

RLD

### Abbreviations

None

### RLD


Instructs the assembler to produce the Relocation Dictionary (RLD) section of the assembler listing. The RLD shows the relocation dictionary information that is passed to the linkage editor or loader, or z/OS binder, in the object module.

### NORLD

Instructs the assembler not to produce the RLD section of the assembler listing.

On z/VSE, you can specify the RLD option on the JCL OPTION statement.

## RXREF



### Default

RXREF

### Abbreviations

RX / NORX

### RXREF

Instructs the assembler to produce the General Purpose Register Cross Reference section of the assembler listing. The General Purpose Register Cross Reference includes:

- The register number
- An indicator showing the context in which the register was used.

**NORXREF**

Instructs the assembler not to produce the General Purpose Register Cross Reference section of the assembler listing.

**SECTALGN**

▶▶—SECTALGN(*alignment*)————▶▶

**Default**

8 (doubleword alignment)

**Abbreviations**

None

**Restrictions**

The GOFF option must be specified if the *alignment* value is greater than 8.

**SECTALGN(*alignment*)**

Specifies the alignment for all sections. The alignment must be a power of 2 between 8 (doubleword) and 4096 (page).

**SEG (CMS)**

▶▶—

SEG
NOSEG

————▶▶

**Default**

None. The assembler modules are loaded from the Logical Saved Segment (LSEG). If the LSEG is not available, the assembler modules are loaded from disk.

**Abbreviations**

None

**Restrictions**

You cannot specify this option on \*PROCESS statements.

You can only specify this option on CMS using the ASMAHL command.


**SEG**

Specifies that the assembler modules are loaded from the Logical Saved Segment (LSEG). If the LSEG is not found the assembler stops.

**NOSEG**

Specifies that the assembler modules may be loaded from disk.

## SIZE



## SIZE(MAX)

## SZ

You cannot specify this option on \*PROCESS statements.

Specifies the amount of virtual storage in 1024-byte (1K) increments.

The minimum acceptable value is 200K (refer to Note 2 on page 75).

Specifies the amount of virtual storage in 1048576-byte (1M) increments.

The minimum acceptable value is 1M.

Specifies that the assembler requests all the available space (refer to Note 3 on page 75) in the user region (z/OS), or virtual machine (CMS) or in the partition GETVIS (z/VSE).

Specifies that the assembler requests all the available space (refer to Note 3 on page 75) in the user region (z/OS), virtual machine (CMS) or partition GETVIS (z/VSE) less the amount of *integerK* of storage (1K equals 1024 bytes).

The minimum acceptable integer  $K$  value is 1K.

Specifies that the assembler requests all the available space (refer to Note 3 on page 75) in the user region (z/OS), or virtual machine (CMS) less the amount of *integerK* of storage (1M equals 1048756 bytes).

The minimum acceptable integerM value is 1M.

1. The maximum storage value you can specify might not be available in the user region (z/OS), virtual machine (CMS), or in the partition GETVIS (z/VSE), after storage has been allocated for the operating system.


2. The minimum amount of working storage required by the assembler is 200K or 10 times the work data set block size, whichever is greater.
3. When you specify the MAX suboption, the assembler releases 128K back to the user region (z/OS), virtual machine (CMS), or the partition GETVIS (z/VSE), for system usage. When you specify the MAX suboption, there might not be enough storage remaining in the user region (z/OS), virtual machine (CMS), or the partition GETVIS (z/VSE), to load any exits you specify, or any external functions you use in your assembly or for operating system functions that may be required during the assembly. If the assembly does fail due to a lack of storage, then use MAX-integerK or MAX-integerM to ensure that there is sufficient free storage during the assembly for any of these functions.
4. The assembler loads user I/O exits before it obtains the working storage. If the user exit obtains storage, then it reduces the amount available for the assembler.
5. The assembler loads external function routines after it obtains working storage. If you use external functions in your program, you should reduce the value you specify in the SIZE option, to allow storage space for the external function modules, and any storage they might acquire.
6. With High Level Assembler R6, the ABOVE operand is obsolete. It is documented here for compatibility. The assembler ignores this operand and always attempts to obtain the storage specified by the SIZE option from above the 16MB line. If storage above the 16MB line is not available, the assembler attempts to obtain the storage from below the 16MB line.

High Level Assembler acquires the amount of storage you specify in the SIZE option from the user region (z/OS), virtual machine (CMS), or partition GETVIS (z/VSE). The assembler only requires a work data set when it has insufficient virtual storage to perform an in-storage assembly. An in-storage assembly usually reduces the elapsed time needed to complete the assembly.

The statistics in the Diagnostic Cross Reference and Assembler Summary section of the assembly listing shows the amount of storage the assembler allocated and the amount of storage the assembler actually used. You should specify a large enough value on the SIZE option to allow the assembler to perform an in-storage assembly, otherwise you must provide a work data set.

To reduce the amount of storage required by the assembly you can disable some of the cross-reference sections of the assembler listing, for example you can specify NOMXREF, NORXREF, or NOXREF. Additionally if ADATA is not required then it should be disabled by specifying NOADATA. Enabling of ADATA processing will cause most of the cross-reference processing to be done, even though the sections will not be output to the assembler listing.

## SUPRWARN



### Default

NOSUPRWARN

### Abbreviations

SUP, NOSUP

### Restrictions

You can only suppress messages of severity 4 or less.

### SUPRWARN

Suppresses the specified message numbers.

### NOSUPRWARN


Reverses the action of SUPRWARN and allows the specified message numbers to be displayed.

### *msgnum*

1–4 digit message number.

If you specify an invalid message number, message ASMA318W is issued. If you specify a message number with a severity higher than 4, message ASMA319W is issued.

## SYSPARM



### Default

The &SYSPARM system variable is set to NULL.

### Abbreviations

None

### Restrictions

You cannot specify this option on \*PROCESS statements.



*string*

Specifies the character string the assembler assigns to the &SYSPARM system variable symbol. The character string is up to 255 characters in length. Any character may be included in the string, subject to the rules for building character strings defined in the *HLASM Language Reference*.

On a z/OS or z/VSE invocation parameter, if the string includes spaces, commas, or parentheses, it must be enclosed in single quotation marks. Any parentheses inside the string must be balanced. You must use two single quotation marks to represent a single quotation mark, and two ampersands to represent a single ampersand. For example:

```
PARM='OBJECT,SYSPARM((&&((AM)), 'E0).FY)'
```


assigns the value (&AM,'E0).FY to &SYSPARM.

on z/OS and z/VSE, JCL restrictions limit the length of the SYSPARM value. When you call the assembler from a problem program (dynamic invocation), you can specify a SYSPARM value up to 255 characters long. The ASMAOPT file ("ASMAOPT options" on page 40) also supports a SYSPARM value up to 255 characters long.

On CMS, you can specify SYSPARM(?). This causes the assembler to issue the following message at your terminal:

```
ENTER SYSPARM:
```

In response to this message you can enter up to 255 characters. To specify a SYSPARM value of ?, you must specify SYSPARM(?) and enter ? at the terminal prompt.

**TERM****Default**

NOTERM

**Abbreviations**

None

**Restrictions**

This option is not allowed on \*PROCESS statements.

**TERM**

Is equivalent to TERM(WIDE). See the description of TERM(WIDE) below.

**WIDE**

On z/OS and CMS, instructs the assembler to write error messages to the terminal data set. You define the terminal data set with the SYSTERM ddname.

On z/VSE, instructs the assembler to write error messages to SYSLOG. SYSLOG is usually assigned at system initialization time and is assigned permanently to the system log (console).

## TERM

### NARROW

The **NARROW** suboption instructs the assembler to compress multiple consecutive spaces into a single space.

On z/OS and CMS, instructs the assembler to write error messages to the terminal data set. You define the terminal data set with the **SYSTEM** ddname.


On z/VSE, instructs the assembler to write error messages to **SYSLOG**. **SYSLOG** is usually assigned at system initialization time and is assigned permanently to the system log (console).

### NOTERM

Instructs the assembler not to write error messages to **SYSTEM** (z/OS and CMS) or **SYSLOG** (z/VSE).

You can specify the **TERM** option on the **JCL OPTION** statement.

## TEST



### Default

**NOTEST**

### Abbreviations

None

### TEST


Specifies that the object module contains the special source symbol table (SYM records) required by the TSO **TEST** command.

### NOTEST

Specifies that the object module does not contain the special source symbol table (SYM records) required by the TSO **TEST** command.

On z/OS and CMS, if you specify the **TEST** option with the **GOFF** option, the assembler ignores the **TEST** option.

## THREAD



### Default

**THREAD**

### Abbreviations

**THR** / **NOTHR**


## THREAD

Specifies that the assembler not reset the location counter to zero at the beginning of each CSECT.

## NOTHREAD

Specifies that the assembler reset the location counter to zero at the beginning of each CSECT, except for the first CSECT when it is initiated by the START instruction having a nonzero operand.

## TRANSLATE



### Default

NOTRANSLATE

### Abbreviations

TR / NOTR

### Restrictions

This option is not allowed on \*PROCESS statements.

### AS

Specifies that characters contained in character (C-type) data constants (DCs) and literals are converted into ASCII characters using the ASCII translation table provided with High Level Assembler.

xx Specifies that characters contained in character (C-type) data constants (DCs) and literals are converted using a user-supplied translation table. The translation table must be named ASMALTxx.


### Notes:

1. Using the TRANSLATE option when you have also specified the DBCS option can cause erroneous translation of double-byte data in C-type constants. G-type constant data is not affected.
2. The assembler searches for the user-supplied translation table load module in the standard load module search order. See also Appendix L, "How to generate a translation table," on page 407.
3. The assembler does not convert UNICODE character strings.

## TYPECHECK

For a detailed description of the TYPECHECK assembler option, see Appendix N, "TYPECHECK assembler option," on page 415.

## TYPECHECK



### Default

`TYPECHECK(MAGNITUDE, REGISTER)`

### Abbreviations

`TC(MAG, NOMAG, REG, NOREG) / NOTC`

### Parameter of ACONTROL statement

You can specify the **TYPECHECK** (or **NOTYPECHECK**) option as a parameter of the **ACONTROL** statement. For further details, refer to “**ACONTROL** statement” in the *HLASM Language Reference*.

### MAGNITUDE

Specifies that the assembler performs magnitude validation of signed immediate-data fields of machine instruction operands.

### NOMAGNITUDE

Specifies that the assembler not perform magnitude validation of signed immediate-data fields of machine instruction operands.

### REGISTER

Specifies that the assembler performs type checking of register fields of machine instruction operands.


### NOREGISTER

Specifies that the assembler not perform type checking of register fields of machine instruction operands.

### NOTYPECHECK

Specifies that the assembler not perform any type checking of machine instruction operands.

## USING

**Default**

USING(MAP, WARN(15))

**Abbreviations**

US / NOUS

**xxxx**

This suboption, when used in combination with the WARN(8) suboption, specifies the maximum displacement that base-displacement address resolution checks.

xxxx is the decimal value of the displacement, and must be less than or equal to 4095. X'xxx' may also be used to specify the value in hexadecimal. If specified, this value must be less than or equal to X'FFF'.

If more than one base register is specified in a USING statement, the value specified in the LIMIT suboption is used only to check the maximum displacement from the last specified base register. For example, if USING(LIMIT(X'F00'), WARN(8)) were specified at invocation, the messages would be issued as in Figure 22 on page 82.

Active Usings: None									
Loc	Object	Code	Addr1	Addr2	Stmt	Source	Statement		
000000			00000	01F82	1	EXAMPLE	CSECT		HLASM R6.0 2008/07/11 17.48 00001000
	R:AB	00000			2		USING EXAMPLE,10,11		00002000
...									
00040E	47F0	AB8C		00B8C	176	B	LABEL111	<b>1</b>	00176000
...									
			00B8C		496	LABEL111 EQU	*		00496000
...									
00152E	47F0	BF80		01F80	908	B	LABEL999	<b>2</b>	00908000
** ASMA304W Displacement exceeds LIMIT value specified									
...									
			01F80		1436	LABEL999 EQU	*		01436000
001F80	07FE				1437	BR	14		01437000
					1438	END			01438000

Figure 22. Effect of the LIMIT suboption

Although the resolved displacement of the instruction at **1** is greater than the specified limit, error diagnostic message ASMA304W is not issued because register 10 was not the last specified base register. However, the instruction at **2** causes the message to be issued because register 11 was the last specified base register.

## NOLIMIT

This suboption specifies that displacements are not checked. Specifying this suboption is equivalent to specifying the LIMIT suboption with a value of 4095 or X'FFF'.

## MAP

This suboption instructs the assembler to produce the USING Map section of the assembler listing. For more information, see “USING map” on page 30.

## NOMAP

This suboption specifies that no USING map is produced.

## WARN(*n*)

This suboption specifies the conditions under which warning error diagnostic messages are issued. Each condition has an associated condition number, *n*. The allowable values for *n* are:

- 0** No USING warning messages are issued.
- 1 Nullified USINGs:** The assembler issues message:
  - ASMA300W when a previous active ordinary (unlabeled) USING’s range coincides with and supersedes that of the USING being processed.
  - ASMA301W when the range of the USING being processed coincides with and supersedes that of a previous active ordinary (unlabeled) USING.
  - ASMA306W when the range of the USING being processed coincides with the implicit USING 0,0 (for example USING 0,2).

**Note:** Message ASMA302W is issued when R0 is specified as a base register with a non-zero base address, and message ASMA306W is issued when any register other than R0 is specified as a base register with an absolute base address whose range overlaps the assembler’s default (0,4095).

- 2 R0 based USINGs:** The assembler issues message ASMA302W when a USING specifies R0 as a base register, with a non-zero absolute or relocatable expression for the base address.

- 4 **Multiple resolutions:** The assembler issues message:
- ASMA303W when multiple resolutions are possible for an implicit address.
  - ASMA306W when the range of the USING being processed overlaps the range of the implicit USING 0,0 (for example USING 16,2).
- Note:** Message ASMA302W is issued when R0 is specified as a base register with a non-zero base address, and message ASMA306W is issued when any register other than R0 is specified as a base register with an absolute base address whose range overlaps the assembler's default (0,4095).
- 8 **LIMIT:** The assembler issues message ASMA304W when the calculated displacement in any valid resolution exceeds the threshold specified in the LIMIT suboption. This has no effect if the LIMIT suboption is not specified.

Several conditions may be combined by adding together the associated condition numbers. For example, specifying WARN(12) would request the assembler to issue warning diagnostic messages for the conditions with condition numbers 4 and 8.

**NOWARN**

This suboption specifies that no USING warning messages are issued.

**NOUSING**

NOUSING specifies that all USING suboptions are off. It is equivalent to specifying USING(NOLIMIT,NOMAP,NOWARN), or specifying in the ASMADOPT default options: LIMIT=NO,MAP=NO,WARN=NO.

The USING suboptions LIMIT, MAP, and WARN are specified in the installation default options as LIMIT, MAP, and WARN.

**WORKFILE**



**Default**

NOWORKFILE

**Abbreviations**

None

**WORKFILE**


If the WORKFILE option is specified, the assembler attempts to assemble the program in central storage. If extra storage is needed, the assembler uses the utility file for temporary storage.

**NOWORKFILE**

If the NOWORKFILE option is specified, the assembly uses only central storage.

## XOBJECT

### XOBJECT (z/OS and CMS)



#### Default


NOXOBJECT

#### Abbreviations

XOBJ / NOXOBJ

**Note:** XOBJECT is treated as a synonym for the GOFF option and accepts the same subparameters as GOFF.

## XREF



#### Default

XREF(SHORT,UNREFS)

#### Abbreviations

None

#### FULL

Instructs the assembler to produce the Ordinary Symbol and Literal Cross Reference section of the assembler listing. This includes symbols that are defined, but never referred to.

#### SHORT

Instructs the assembler to produce the Ordinary Symbol and Literal Cross Reference section of the assembler listing. Symbols that are defined, but not referred to, are not included in the cross reference listing. SHORT may be specified with the UNREFS suboption to produce a list of unreferenced symbols. The SHORT suboption can not be specified with the FULL suboption.

#### UNREFS

Instructs the assembler to produce the Unreferenced Symbols Defined in CSECTs section of the assembler listing. The symbols are listed in symbol name order. UNREFS may be specified with the SHORT suboption to produce a cross reference list of referenced symbols. The UNREFS suboption can not be specified with the FULL suboption.



**NOXREF**

Specifies that symbol cross reference information is not generated as part of the assembly listing.

Any suboption you specify overrides the suboptions specified in the installation default options, unless the XREF option is fixed.

If you specify the XREF option more than once, the assembler uses the last one you specify. For example, if you specify XREF(SHORT),XREF(UNREFS), the assembler uses XREF(UNREFS). To use both suboptions, specify XREF(SHORT,UNREFS).

On z/VSE, you can use the XREF option of the JCL OPTION statement to specify the XREF(FULL) assembler option, and the SXREF option of the JCL OPTION statement to specify the XREF(SHORT) assembler option.



---

## Chapter 4. Providing user exits

This chapter describes how you can provide user exits to complement the assembler's data set processing. It describes the type of exits, how to specify them during assembly, and the details you need to write an exit.

---

### Exit types

You can instruct the assembler to call these types of exits:

#### **SOURCE Exit**

To process Primary Input records.

You use a SOURCE exit to replace or complement the assembler's primary input data set processing. You can use it to supply primary input records to the assembler, or monitor and modify records the assembler has read before the assembler processes them. The exit can supply all the primary input records, or extend the primary input by supplying additional records during the assembly. The exit can also discard records.

#### **LIBRARY Exit**

To process Library Input records.

You use a LIBRARY exit to replace or complement the assembler's macro call (MACRO) and copy code (COPY) library processing. You can use it to supply MACRO and COPY library records to the assembler, or monitor and modify records the assembler has read before the assembler processes them. The exit can supply all the MACRO and COPY library records, or extend the library input processing by supplying additional MACRO and COPY records during the assembly. The exit can also discard records.

#### **LISTING Exit**

To process Listing Output records.

You use a LISTING exit to replace or complement the assembler's listing output processing. You can use it to write the listing records the assembler supplies, or monitor and modify the records before the assembler writes them to the listing data set. The exit can write all the listing records, or supply additional listing records for the assembler to write during the assembly. The exit can also discard records.

#### **OBJECT (z/OS and CMS) and PUNCH Exit**

To process Object and Punch Output records.

You use an OBJECT and PUNCH exit to replace or complement the assembler's object module output processing. You can use it to write the object module records the assembler supplies, or monitor and modify the records before the assembler writes them to the object data set. The exit can write all the object module records, or supply additional records for the assembler to write during the assembly. The exit can also discard records.

#### **ADATA Exit**

To process Associated Data Output records.

You use an ADATA exit to replace or complement the assembler's associated data output processing. You can use it to write the associated data records the assembler supplies, or monitor and modify the records

## Exit types

before the assembler writes them to the associated data data set. The exit can write all the associated data records, or supply additional records for the assembler to write during the assembly. The exit can also discard records.

### TERM Exit

To process Terminal Output records.

You use a TERM exit to replace or complement the assembler's terminal output processing. You can use it to write the terminal records the assembler supplies, or monitor and modify the records before the assembler writes them. The exit can write all the terminal records, or supply additional terminal records for the assembler to write during the assembly. The exit can also discard records.

**z/VSE**

The assembler writes terminal output to SYSLOG; however, you can use the exit to write the output to a disk data set.

**End of z/VSE**

## Specifying user exits

You use the EXIT option to specify the name of one or more user exits to load, and optionally pass to the exit a character string up to 64 characters long that is processed during assembly initialization. You can use the EXITCTL assembler instruction to pass data from the assembler source program to the user exit during the assembly. See "EXITCTL" on page 94.

The Diagnostic Cross Reference and Assembler Summary section of the assembler listing shows the statistics for records processed by the user exits during the assembly. See "EXIT" on page 51 for the syntax of the EXIT assembler option.

These tables lists the exit type, the EXIT suboption, the default data set *ddname* (z/OS and CMS), or *filename* (z/VSE), that the exit corresponds to, and a Page number reference to the section that describes how the assembler processes the exit:

*Table 9. z/OS and CMS exit types*

Exit Type	Exit Suboption	<i>ddname</i>	Page Number
SOURCE	INEXIT	SYSIN	104
LIBRARY	LIBEXIT	SYSLIB	106
LISTING	PRTEXIT	SYSPRINT	112
PUNCH	OBJEXIT	SYSPUNCH	116
OBJECT	OBJEXIT	SYSLIN	116
ADATA	ADEXIT	SYSADATA	120
TERM	TRMEXIT	SYSTEM	123

*Table 10. z/VSE exit types*

Exit Type	Exit Suboption	<i>filename</i>	Page Number
SOURCE	INEXIT	IJSYSIN	104

Table 10. z/VSE exit types (continued)

Exit Type	Exit Suboption	filename	Page Number
LIBRARY	LIBEXIT	Library sublibraries	106
LISTING	PRTEXTIT	IJSYSLS	112
PUNCH	OBJEXIT	IJSYSPH	116
ADATA	ADEXIT	SYSADAT	120
TERM	TRMEXIT	SYSLOG	123

## Loading user exits

The assembler loads the user exits during initialization. The assembler must be able to locate the user exits as follows:

### z/OS

The user exit must be a load module or program object that is located in a partitioned data set in the standard search sequence. The user exit can also be located in the Link Pack Area (LPA).

An exit module may contain more than one entry name if the initially loaded module executes an IDENTIFY macro to make additional names available to the assembler as exit names.

If you use the same exit load module for more than one user exit type, for example as a SOURCE and LISTING exit, the load module can be loaded more than once, depending on the link edit options specified.

### End of z/OS

### z/VM

The user exit must be a MODULE that is located on one of the accessed disks. You generate the module using the CMS LOAD and GENMOD commands. When the LOAD command is issued, the RLDSAVE option must be specified to make the module relocatable. If RLDSAVE is not specified, it might result in the assembler program or data storage being overlaid.

If you use the same exit load module for more than one user exit type, for example as a SOURCE and LISTING exit, only one copy of the module is loaded.

### End of z/VM

### z/VSE

The user exit must be a relocatable phase that is in a sublibrary you specify in your JCL LIBDEF phase search chain. The user exit can also be located in the Shared Virtual Area (SVA).

If you use the same exit for more than one exit type, for example as a SOURCE and LISTING exit, only one copy of the phase is loaded.

### End of z/VSE

## Loading user exits

The user exits may be created in any addressing mode (AMODE) and residency mode (RMODE).

---

## Calling user exits

The assembler calls user exits using the standard OS Linkage conventions. The user exit can be written in any language that conforms to these constraints:

- Can be called many times via the exit module entry point
- Retains storage for private variables across invocations

High Level Assembler provides an “anchor word” in the Exit Parameter List to allow you to maintain information across calls to the exit.

Refer to the language’s *Programming Guide* to find out if you can use it to write a user exit for the assembler.

The contents of the registers upon entry to the user exit are as follows:

<b>Register 0</b>	Undefined
<b>Register 1</b>	Address of Exit Parameter List, see Figure 23 on page 91.
<b>Registers 2 through 12</b>	Undefined
<b>Register 13</b>	Address of 72 byte save area
<b>Register 14</b>	Return address
<b>Register 15</b>	Address of entry point of user exit

---

## Exit parameter list

The assembler passes an Exit Parameter List to the user exit. On entry to the exit, Register 1 contains the address of this parameter list. Each exit is passed a separate copy of the parameter list. The parameter list includes a pointer to an Exit-Specific block that contains information for each exit type. High Level Assembler provides macro ASMAXITP to map the Exit Parameter List and the Exit-Specific Information block. Figure 23 on page 91 describes the format of the Exit Parameter List, Figure 24 on page 101 describes the format of the Exit-Specific Information block for the LISTING exit, and Figure 25 on page 101 describes the format of the Exit-Specific Information block for the other exit types.

| The high-order bit of the last pointer in the I/O exit parameter list is set to 1.

| The HLASM Services Interface for I/O exits is described Appendix O, “HLASM Services Interface,” on page 427.

|




Figure 23. Exit parameter list format

The following sections describe the Exit Parameter List.

### Request info pointer

The request info pointer points to a list of fullword fields that describe the exit request. The assembler sets this pointer, which is always a valid address.

### Parameter list version

A fullword identifying the version of the parameter list. For High Level Assembler Release 6 this field contains a value of 3.

## Exit parameter list

### Exit type

A fullword identifying the type of exit being called. You use this field when the exit handles more than one exit type. The exit type is identified by the following values:

- 1 SOURCE Input
- 2 LIBRARY Input
- 3 LISTING Output
- 4 PUNCH Output
- 5 OBJECT Output
- 6 ADATA Output
- 7 TERM Output

The assembler always sets this field.

### Request type

A fullword identifying the type of processing request. The request type is identified by these values:

- 1 OPEN—exit receives control before any input or output processing.
- 2 CLOSE—exit receives control before the assembler does any close processing.
- 3 READ—exit receives control to provide a record to the assembler.
- 4 WRITE—exit receives control to write a record provided by the assembler.
- 5 PROCESS (for exit types other than LIBRARY)—exit receives control to inspect or manipulate the record provided by the assembler.
- 5 PROCESS MACRO (LIBRARY exit type)—exit receives control to inspect or manipulate the macro definition record provided by the assembler.
- 6 PROCESS COPY (LIBRARY exit type)—exit receives control to inspect or manipulate the copy member record provided by the assembler.
- 7 FIND MACRO (LIBRARY exit type)—exit receives control to locate the specified library macro.
- 8 FIND COPY MEMBER (LIBRARY exit type)—exit receives control to locate the specified copy member.
- 9 END OF MEMBER (LIBRARY exit type)—exit receives control after the reading of a macro or copy member is completed.
- 10 REINIT—exit receives control during the assembler's reinitialisation processing between assemblies in a batch. This call only occurs if the exit requested the REINIT by setting reason code 16 in response to the OPEN request.

The assembler always sets this field.

### Options

A fullword that provides additional information to the exit.

**For the SOURCE and LIBRARY exits:** These values are provided:

- 0 No additional information available.



- 1 New information is available in the Exit-Specific Information block. The assembler updates this block whenever the primary input data set changes.  
For example, the SOURCE input might be a concatenation of data sets. When the first data set is opened, and when each subsequent concatenated data set is opened, this value is set to 1 to inform the exit that a data set switch has occurred. It is also set for LIBRARY processing to inform the exit which data set in the concatenation is being used to provide the specific member.
- 2 For the LIBRARY exit, when the request type is FIND MACRO or FIND COPY, this indicates that the copy code or a macro should resume at the saved record position.
- 3 For the LIBRARY exit, when the request type is FIND MACRO or FIND COPY, this indicates that copy code or a macro definition is currently being processed. The user exit should save the position within the current member to allow it to be resumed when the new member has been processed.

See “Nesting COPY instructions and macro definitions” on page 110.

**For the LISTING exit:** These decimal values are provided:

- 00 No additional information available
- 10 High Level Assembler Options Summary heading line
- 11 High Level Assembler Options Summary detail line
- 15 High Level Assembler Options Summary diagnostic message
- 17 High Level Assembler Product Information heading line
- 18 High Level Assembler Product Information detail line
- 20 External Symbol Dictionary heading line
- 21 External Symbol Dictionary detail line
- 30 Source and Object heading line
- 31 Source and Object machine instruction
- 32 Source and Object DC/DS instruction
- 33 Source and Object comment
- 34 Source and Object statement in error
- 35 Source and Object diagnostic message
- 36 Source and Object other
- 40 Relocation Dictionary heading line
- 41 Relocation Dictionary detail line
- 50 Ordinary Symbol and Literal Cross Reference heading line
- 51 Ordinary Symbol and Literal Cross Reference detail line
- 52 Unreferenced Symbols Defined in CSECTs heading line
- 53 Unreferenced Symbols Defined in CSECTs detail line
- 60 Macro and Copy Code Source Summary heading line
- 61 Macro and Copy Code Source Summary detail line
- 62 Macro and Copy Code Cross Reference heading line
- 63 Macro and Copy Code Cross Reference detail line
- 70 DSECT Cross Reference heading line
- 71 DSECT Cross Reference detail line
- 80 USING Map heading line
- 81 USING Map detail line
- 85 General Purpose Register Cross Reference heading line
- 86 General Purpose Register Cross Reference detail line
- 90 Diagnostic Cross Reference and Assembler Summary heading line
- 91 Diagnostic Cross Reference and Assembler Summary detail line

**For the PUNCH, OBJECT, and ADATA exits:** This field contains 0.

## Exit parameter list

The assembler sets this field.

### EXITCTL*n*

Four fullword fields containing the exit-control values for this exit type. Exit-control values are set by the EXITCTL assembler instruction during the assembly.

**For the SOURCE and LIBRARY exits:** The new EXITCTL values are available to the exit when the input record after the EXITCTL instruction is passed to the exit.

**For the LISTING, ADATA, and TERM exits:** The new EXITCTL values are available to the exit with the output record containing the EXITCTL instruction.

**For the OBJECT and PUNCH exits:** The new EXITCTL values are available to the exit when the next object module record is passed to the exit. This may happen several source statements after the EXITCTL instruction statement. A possible consequence is that one or more EXITCTL statements can be processed without the exit receiving the EXITCTL parameter values, if they occur between object records.

### Return code

A fullword, set by the exit, that indicates success or failure of the exit call, and the action taken by the assembler on return from the exit. Table 11 summarizes the return codes.

Return code 20 is described at “Error handling” on page 100.

Table 11. User-exit return codes

Exit	Request	RC=0	4	8	16	20 <sup>7</sup>
SOURCE	OPEN	Assembler to open the primary input data set <sup>1</sup>	Exit provides records <sup>2</sup>		Disable <sup>6</sup>	Operation failed
	CLOSE	Operation successful				Operation failed
	READ	Exit has provided record			End-of-file indicator	Operation failed
	PROCESS	Accept record	Discard record		Disable <sup>6</sup>	Operation failed
	REINIT	Operation successful			Disable <sup>6</sup>	Operation failed
LIBRARY	OPEN	Assembler to open its library <sup>1</sup>	Exit has opened its library <sup>3</sup>	Exit has opened its library, assembler to open its library	Disable <sup>6</sup>	Operation failed
	CLOSE	Operation successful				Operation failed
	READ	Exit has provided record			EOD on input source	Operation failed
	PROCESS (macro or copy member)	Accept record	Discard record		Disable <sup>5, 6</sup>	Operation failed
	FIND (macro or copy member)	Operation successful	Member not found; search assembler library if available			Operation failed
	END OF MEMBER	Operation successful			Disable <sup>5, 6</sup>	Operation failed
	REINIT	Operation successful			Disable <sup>6</sup>	Operation failed

Table 11. User-exit return codes (continued)

Exit	Request	RC=0	4	8	16	20 <sup>7</sup>
LISTING PUNCH OBJECT(z/OS and CMS) TERM ADATA	OPEN	Assembler opens the output data set <sup>1</sup>	Exit has opened its output data set <sup>4</sup>		Disable <sup>6</sup>	Operation failed
	CLOSE	Operation successful				Operation failed
	WRITE	Exit has written record				Operation failed
	PROCESS	Accept record	Discard record		Disable <sup>6</sup>	Operation failed
	REINIT	Operation successful			Disable <sup>6</sup>	Operation failed

**Notes:**

1. The assembler only uses the PROCESS and CLOSE operation codes on subsequent calls.
2. The assembler only uses the READ and CLOSE operation codes on subsequent calls.
3. The assembler only uses the READ, FIND, and CLOSE operation codes on subsequent calls.
4. The assembler only uses the WRITE and CLOSE operation codes on subsequent calls.
5. This return is valid from all PROCESS and END OF MEMBER requests, with these exceptions:
  - a. PROCESS MACRO requests when the LIBRARY exit set the return code of 8 for the OPEN request.
  - b. PROCESS COPY requests when the LIBRARY exit set the return code of 8 for the OPEN request.
  - c. END OF MEMBER requests when the LIBRARY exit set the return code of 4 or 8 for the OPEN request.
6. If an exit sets the disable return code, then the assembler does not call that exit again, so any resource clean-up should be done before returning control to the assembler.
7. See "Error handling" on page 100.

**Reason code**

A fullword, set by the exit, to qualify the return code. Table 12 shows reason codes for each exit type, and which request they are checked after.

Table 12. User exit reason codes

Exit	Request	RSN=0	4	8	16
SOURCE	OPEN	No additional information	Input source information available		REINIT call required
	READ	No additional information	Input source information available	Redrive requested <sup>2</sup>	
LIBRARY	OPEN	No additional information	End of member call required		REINIT call required
	FIND (macro or copy member)	No additional information	Input source information available	Redrive requested <sup>2</sup>	
	READ	No additional information	Input source information available	Redrive requested <sup>2</sup>	
LISTING TERM	OPEN	No additional information	When return code is 0, reason code 4 indicates the exit has provided a line length in the buffer length field. When return code is 4, reason code 4 indicates the exit has provided the data set information.		REINIT call required

## Exit parameter list

Table 12. User exit reason codes (continued)

Exit	Request	RSN=0	4	8	16
SOURCE LIBRARY LISTING PUNCH OBJECT(z/OS and CMS) TERM ADATA	PROCESS	No additional information	Return to exit with empty buffer	Redrive requested <sup>2</sup>	
LISTING PUNCH OBJECT(z/OS and CMS) TERM ADATA	WRITE	No additional information		Redrive requested <sup>2</sup>	
PUNCH OBJECT(z/OS and CMS)	OPEN	No additional information	Exit has provided the output data set information		REINIT call required
ADATA	OPEN	No additional information	Exit has provided the output data set information	Exit intends to discard type X'0002' and X'0090' records	REINIT call required

**Notes:**

1. Multiple reason codes can be specified by OR-ing them together.
2. When redrive is requested, the assembler issues any required error message and then recalls the exit with the same parameter list as before.

### Buffer length

A fullword containing the length of the area pointed to by the buffer pointer.

**For OPEN requests:** This field contains the length of the optional character string you specified in the EXIT assembler option.

**For WRITE and PROCESS requests:** This field contains the length of the record pointed to by the buffer pointer.

**For READ requests:** This field contains the length of the area pointed to by the buffer pointer where the exit may return a record to the assembler.

**All other requests:** This field contains zero.

**Setting the length:** When either the SOURCE, LIBRARY, PUNCH, or OBJECT exit is invoked for a READ, WRITE, or PROCESS request, the assembler sets the buffer length to 80.

On z/OS and CMS, if you specify the GOFF assembler option, and the OBJECT exit is invoked, the buffer length might be fixed-length 80, or variable-length, depending on the JCL (z/OS) you supply. The maximum value for variable-length records is 8212.

For an OPEN request the LISTING exit can use this field to pass the listing line length to the assembler. The exit indicates that it has provided a print line length by setting the return code to 0 and the reason code to 4.

### z/VM and z/OS

The line length must be in the range 121 to 255. If it is any other value, the

assembler issues message ASMA402W and does not call the exit to process listing records.

End of z/VM and z/OS

z/VSE

If the assembler opens the listing data set and the LISTING exit provides a print line length, the line length must be 121 if SYSLST is assigned to disk, otherwise it can be any value from 121 to 133. If it is any other value, the assembler issues message ASMA402W and does not call the exit to process listing records.

End of z/VSE

For all other calls to the LISTING exit, the assembler sets this field to the length determined during the OPEN call.

The TERM exit can use this field to indicate to the assembler the length of the terminal record. This may be done when the exit is invoked with an OPEN request. The exit indicates that it has provided a terminal line length by setting the Return Code to 0 and the Reason Code to 4. The value must not be zero, or negative, and must not be greater than 255 on z/OS and CMS, or 125 on z/VSE. If the value is not correct, the assembler issues message ASMA404W and does not call the exit to process terminal records.

For all other calls to the TERM exit, the assembler sets this field to the length determined during the OPEN call.

### Error buffer length

An unsigned fullword, set by the exit, that contains the length of the text pointed to by the error buffer pointer. The maximum length is 255 bytes. If the exit specifies a larger value, the assembler uses 255.

The assembler uses this length to determine whether to issue an error message. If the length is greater than zero, the text in the error buffer is inserted into one of the messages ASMA700I to ASMA704C. The assembler selects which message to issue by checking the value of the error severity field.

The contents of the error buffer are ignored on CLOSE calls to the exit, unless the exit requests immediate termination. If immediate termination is requested, the assembler generates an ASMA940U message with the text provided by the exit; all remaining open exits are CLOSED, but may not provide any additional message text.

### Error severity

A fullword, set by the exit, that contains the severity code the assembler uses to determine which diagnostic message to issue.

The severity code should be a value of 0, 4, 8, 12, or 16. If the severity code is not one of these values, it is rounded up to the nearest value or, if the severity code is greater than 16, it is reset to 16.

The values 0, 4, 8, 12, and 16 correspond to the five diagnostic messages, ASMA700I through ASMA704C, respectively. For example, severity code of 4 causes the assembler to issue message ASMA701W. Table 13 on page 98 summarizes the return code values and the associated diagnostic message.

Table 13. Error severity and associated diagnostic message

Error Severity Code Specified	Error Severity Code Used	Associated Message
0	0	ASMA700I
1–4	4	ASMA701W
5–8	8	ASMA702E
9–12	12	ASMA703S
> 12	16	ASMA704C

### User-defined field

A fullword, set to zero by the assembler before it calls the exit with an OPEN request. The exit can use this field to store information (such as the address of acquired storage) between calls. This field is separately maintained for each exit type and is preserved across all calls until the exit is closed. The assembler does not modify or interpret this field.

### Common user field

A fullword, set to zero by the assembler. Any exit can use this to store information (such as the address of acquired storage) between calls. This field is common for all exit types and so provides a mechanism for different exits to share information. The assembler does not modify or interpret this field.

## Buffer pointer

The buffer pointer points to the area containing a record to be processed by the exit.

*For OPEN Requests:* This field contains the character string from the EXIT assembler option. If you did not specify a character string in the EXIT assembler option, this area contains spaces and the buffer length field is set to zero.

*For READ Requests:* This field points to an empty buffer area.

*For PROCESS and WRITE Requests:* This field points to the record supplied by the assembler.

*All Other Requests:* This field is set to zero.

**Note:** The buffer pointer may not be the same for all calls to the exit, even if the exit is the same type for all calls.

## Error buffer pointer

The error buffer pointer points to the error text buffer.

The assembler sets this pointer. If you want the assembler to issue a message on behalf of the exit, you must supply the text of the error messages in the area pointed to by the error buffer pointer. The text can be up to 255 characters. The exit must place the length of the text in the error buffer length field. The assembler selects a message number based on the value you place in the error severity field.

## Exit-specific information pointer

The exit-specific information pointer is a fullword that contains the address of the Exit-Specific Information block. The assembler sets this pointer. For more details, see “Exit-Specific Information Block” on page 100.

## DCB pointer

z/VSE

This field is a fullword and always contains zeros. It is included to maintain compatibility with the Exit Parameter List in the z/VM and z/OS environments.

End of z/VSE

z/VM and z/OS

The DCB pointer is a fullword that contains the address of the Data Control Block.

End of z/VM and z/OS

The assembler sets this address which points to the applicable DCB for the exit being called as follows:

Exit	DCB
SOURCE	SYSIN
LIBRARY	SYSLIB
LISTING	SYSPRINT
PUNCH	SYSPUNCH
OBJECT	SYSLIN
ADATA	SYSADATA
TERM	SYSTEMR

When an exit is invoked with an OPEN request, the data set referred to by the DCB is not open, and the contents of the DCB might not be complete.

When an exit is invoked with a PROCESS request, the exit may use the DCB to obtain additional information about the data set or member being used. For example, on z/OS, the exit can obtain user information from a PDS or PDSE directory by using the BLDL system macro.

## Static assembler information pointer

The Static Assembler Information Pointer is a fullword that contains the address of the Static Assembler Information block. The block is not aligned on any particular boundary.

### HLASM VRM

This is an 8 byte field which contains the version, release and modification level of the assembler being used to assemble the source module. For example, when HLASM Release 5.0 is being used, this field has the value “1.5.0”. The value of the field is set to the value of the system variable &SYSVER.

### PTF level

This is an 8 byte field which contains the current PTF level of the assembler being used to assemble the source module. For example, when the last PTF applied to the assembler was UQ12345 this field will have the value: UQ12345.

### System ID

This is a 16 byte field which contains the name and release of the operating system under which your source module is being assembled. For example, on an MVS™ system, the field might contain the value “MVS/ESA SP 5.1.0”. The value of the field is set to the value of the system variable &SYSTEM\_ID.

### Numeric version

A fullword containing a numeric value indicating the version and release of the assembler being used. For example, for High Level Assembler Release 5, this field is set to 5.

## HLASM Services Interface pointer

HLASM Services Interface pointer is a fullword that contains the address of the HLASM Services Interface block. For more information see Appendix O, “HLASM Services Interface,” on page 427.

---

## Error handling

**Exit Failure Handling:** You can signal an exit failure for any call to the exit by setting the return code field in the Exit Parameter List to 20. When the assembler receives this return code it issues message ASMA940U, and stops the assembly. You can provide the assembler with additional information to insert in the message text by placing the information in the error buffer pointed to by error buffer pointer, and the length of the information in the error buffer length.

If the exit sets the return code field in the Exit Parameter List to any value other than those described in Table 11 on page 94, the assembler issues message ASMA940U and stops the assembly.

**Note:** For CLOSE requests, the assembler only checks for a return code of 20; it treats all other values as a successful completion.

**User Error Handling:** You can instruct the assembler to produce an error message after any call to the exit by placing information in the error buffer pointed to by error buffer pointer, and the length of the information in the error buffer length. You can indicate the severity of the message by placing the severity code in the error severity field. The message is issued as a normal assembler message and, as such, can be suppressed using the FLAG assembler option.

---

## Exit-Specific Information Block

All user exits are passed an Exit-Specific Information block pointed to by the Exit Parameter List. It contains a list of character data items which describe the data for the exit, and the absolute and relative record numbers for the record passed to the exit.

On entry to the exit, the Member Name field contains spaces (unless the data set is a SYSLIB data set), the Data Set Name field contains the path name, and the Volume Serial field contains spaces.



The Exit-Specific Information block passed to all exits, except the LISTING exit, is shown in Figure 25. The Exit-Specific Information block passed to the LISTING exit has additional parameters as shown in Figure 24.




Figure 24. Exit-specific information block—LISTING exit




Figure 25. Exit-specific information block—other exit types

The Exit-Specific Information block consists of these fields:

**Member Name**

Member name within the data set. It is always provided for library

## Exit-Specific Information Block

members and is also provided for data set members used sequentially on z/OS where the data set is a partitioned data set.

The assembler also sets this field as a parameter for the FIND operation. It is left-justified and padded with spaces.

For output files, the information should not be updated after it has been set by the OPEN call.

The assembler uses this field to update the system variable symbols, as described in Table 14 (z/OS and CMS) and Table 15 (z/VSE).

### Member Type

#### z/VM and z/OS

Always blank. This field is present to maintain compatibility with High Level Assembler running on z/VSE.

End of z/VM and z/OS

#### z/VSE

The file type of the member. This field is also set by the assembler as a parameter for the FIND operation. It is left-justified and padded with spaces.

End of z/VSE

### Data Set Name

The name of the data set from which the last input record was retrieved, or to which the next output record is written. It is left-justified and padded with spaces.

#### z/VSE

For library data sets, the name includes the library and sublibrary name.

End of z/VSE

For output files, the information should not be updated after it has been set by the OPEN call.

The assembler uses this field to update the system variable symbols, as described in Table 14 (z/OS and CMS) and Table 15 (z/VSE).

### Volume Serial

Volume serial where the data set is located. It is left-justified and padded with spaces.

For output files, the information should not be updated after it has been set by the OPEN call.

The assembler uses this field to update the system variable symbols, as described in Table 14 (z/OS and CMS) and Table 15 (z/VSE).

Table 14. z/OS and CMS system variable symbols

Data Set	Member Name	Data Set Name	Volume Serial
SYSIN	&SYSIN_MEMBER	&SYSIN_DSN	&SYSIN_VOLUME
SYSLIB	&SYSLIB_MEMBER	&SYSLIB_DSN	&SYSLIB_VOLUME

Table 14. z/OS and CMS system variable symbols (continued)

Data Set	Member Name	Data Set Name	Volume Serial
SYSPRINT	&SYSPRINT_MEMBER	&SYSPRINT_DSN	&SYSPRINT_VOLUME
SYSTEM	&SYSTEM_MEMBER	&SYSTEM_DSN	&SYSTEM_VOLUME
SYPUNCH	&SYPUNCH_MEMBER	&SYPUNCH_DSN	&SYPUNCH_VOLUME
SYSLIN	&SYSLIN_MEMBER	&SYSLIN_DSN	&SYSLIN_VOLUME
SYSADATA	&SYSADATA_MEMBER	&SYSADATA_DSN	&SYSADATA_VOLUME

Table 15. z/VSE system variable symbols

Data Set	Member Name	Data Set Name	Volume Serial
SYSIPT (IJSYSIN)	&SYSIN_MEMBER	&SYSIN_DSN	&SYSIN_VOLUME
Library	&SYSLIB_MEMBER	&SYSLIB_DSN	&SYSLIB_VOLUME
SYSLS (IJSYLS)	&SYSPRINT_MEMBER	&SYSPRINT_DSN	&SYSPRINT_VOLUME
SYSLOG	&SYSTEM_MEMBER	&SYSTEM_DSN	&SYSTEM_VOLUME
SYPCH (IJSYPH)	&SYPUNCH_MEMBER	&SYPUNCH_DSN	&SYPUNCH_VOLUME
SYSADAT	&SYSADATA_MEMBER	&SYSADATA_DSN	&SYSADATA_VOLUME

**Relative Record Number**

The relative record number is the number assigned to the current record being processed.

**PROCESS Calls**

For PROCESS calls, it represents the total number of records the assembler has passed to the exit for the current data set. Each time a new data set or library member is opened for input, the relative record number is reset to 1 for the first record. If the new data set is a library member, caused by a macro call or a COPY instruction, the relative record number is returned to the correct sequential number when the macro or COPY processing is complete.

**LISTING Exit**

The relative record number is reset to 1 for the LISTING exit whenever the assembler forces a page eject.

**BATCH Assembler Option**

The relative record number is reset to 1 for all output data sets prior to each assembly when the BATCH assembler option is specified.

**READ and WRITE Calls**

For READ calls and WRITE calls, the exit should maintain the relative record number. The assembler uses the relative record number in information messages when you specify the FLAG(RECORD) option. If you specify the ADATA option, the assembler includes the record number in the associated data file (ADATA) Source Analysis record.

**Absolute Record Number**

The absolute record number is the number assigned to the current record being processed. The number is incremented by 1 for each record since the assembly started. For PROCESS calls, it represents the total number of records provided to the exit for the current exit type. It starts at 1, but is not reset when the BATCH assembler option is specified to assemble multiple source programs.

## Exit-Specific Information Block

For READ calls and WRITE calls, the exit should maintain the absolute record number. The number provided after READ calls is written to the associated data file (ADATA) in the Source Analysis record.

### Linecount

This field is only provided for the LISTING exit.

The linecount value is set to the value of the LINECOUNT assembler option before the OPEN call to the LISTING exit. This option contains the number of lines per page in the assembler listing. The exit may change the linecount value only during the OPEN call.

For PROCESS calls, the linecount field contains the number of logical records written to the current listing page. A page eject occurs when the number exceeds the linecount value specified in the LINECOUNT assembler option or during the OPEN call.

### Current Page Number

The assembler sets this field to the value of the current page number. Any change the exit makes to this number is ignored.

This field is only provided for the LISTING exit and only for the PROCESS, WRITE and CLOSE call types.

---

## SOURCE exit processing

The assembler calls the SOURCE exit with these request types:

### OPEN

The assembler calls the exit with a request type of 1 (OPEN) at the start of the assembly. This is the first call to the exit.

The exit may set the return code in the Exit Parameter List to one of these:

- 0 Instructs the assembler to open the primary input data set, and supply the primary input records to the exit in later PROCESS calls.

**Note:** A reason code of 16 indicates a REINIT call is required.

- 4 Indicates that the exit supplies the primary input records to the assembler in later READ calls. If you wish to provide the assembler with the values for the system variables &SYSIN\_DSN, &SYSIN\_MEMBER and &SYSIN\_VOLUME, the user exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. The assembler also shows this information in the Diagnostic Cross Reference and Assembler Summary section of the listing, and includes it in the associated data file Job Identification record.

**Note:** A reason code of 16 indicates a REINIT call is required.

- 16 Instructs the assembler to open the primary input data set, and make no further calls to the exit.

If you provide a character string in the *str1* suboption of the EXIT assembler option, the buffer pointer points to the character string, and buffer length contains the length of the character string. The buffer length is set to zero if there is no character string.

## CLOSE

The assembler calls the exit with a request type of 2 (CLOSE) at the end of the assembly. The exit should close any data sets it opened and release any storage that it acquired.

## READ

The assembler calls the exit with a request type of 3 (READ) when the exit is supplying the primary input records.

The exit may set the return code in the Exit Parameter List to one of these:

- 0 A record is supplied. The record must be placed in the area pointed to by the buffer pointer field. The record area is 80 characters in length.

The user exit should maintain the absolute record number and the relative record number. These fields are set to zero before the OPEN request. The assembler uses the relative record number in diagnostic messages when you specify the FLAG(RECORD) assembler option. If you specify the ADATA assembler option, the assembler includes both fields in the associated data file Source Analysis record.

If you wish to provide the assembler with the values for the system variables &SYSIN\_DSN, &SYSIN\_MEMBER and &SYSIN\_VOLUME, the user exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. You can provide this information during the OPEN call, or whenever the exit supplies a record to the assembler. If the exit is reading records from concatenated data sets, it should supply the data set information with the first record from each data set in the concatenation.

If the exit does not supply the data set information, the system variables are set to null, and the primary input data set details are not shown in the Diagnostic Cross Reference and Assembler Summary section of the listing, nor are they included in the ADATA Job Identification record.

- 16 Indicates to the assembler that there are no more records. This is equivalent to end-of-file processing for input data sets.

## PROCESS

The assembler calls the exit with a request type of 5 (PROCESS) when the assembler is reading the primary input data set, and it has a record for the exit to process. The address of the record read is in the buffer pointer field, and the length is in the buffer length field. The record length is always 80.

The exit can set the return code in the Exit Parameter List to one of these:

- 0 Indicates that the record has been accepted, and the assembler is to process it. The exit may modify the record before it returns control to the assembler. The user exit may also insert extra records in the primary input by setting the reason code to 4. The assembler processes the current record and then calls the user exit with an empty buffer. The exit must place the record in the 80-byte area pointed to by the buffer pointer field. The exit can continue to supply additional records, by setting the reason code to 4. The exit must keep track of when the assembler calls it with an empty buffer, and ensure that it resets the reason code to zero to resume normal processing.
- 4 Instructs the assembler to discard the current record.

## SOURCE exit processing

16 Instructs the assembler to make no further calls to the exit.

Although the user exit might insert or discard records, the assembler maintains the absolute record number and relative record number.

If the options field is set to 1 (see “Options” on page 92), the assembler has provided the exit with the current primary input data set information in the data set name, member name, and volume serial fields of the exit-specific information block. The assembler updates this information when it reads the first record of each data set in a data set concatenation.

Table 16 summarizes the SOURCE exit processing.

*Table 16. SOURCE exit processing summary*

Request Value=Type	Exit Return Code	Action
1=OPEN	0	Assembler opens primary input.
	4	Exit supplies primary input records. If reason code=4, exit supplies data set information. If reason code=16, REINIT call required.
	16	Assembler opens primary input, and makes no further calls to the exit.
2=CLOSE	n/a	Exit should close any data sets it opened, and release any storage it acquired.
3=READ	0	Exit supplies record in buffer. If reason code=4, exit supplies data set information. If reason code=8, redrive requested. <sup>1</sup>
	16	Exit indicates end-of-file.
5=PROCESS	0	Record accepted. Exit may modify record. If reason code=4, the assembler, after processing the current record, provides an empty buffer for the exit to provide additional record. If reason code=8, redrive requested. <sup>1</sup>
	4	Requests assembler to discard record. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.
10=REINIT	0	Operation successful.
	16	Assembler makes no further calls to the exit.

**Notes:**

1. When redrive is requested, the assembler issues any required error message and then recalls the exit with the same parameter list as before.

## LIBRARY exit processing

The assembler calls the LIBRARY exit with the following request types:

### OPEN

The assembler calls the exit with a request type of 1 (OPEN) at the start of the assembly. This is the first call to the exit.

The exit can set the return code in the Exit Parameter List to one of the following:

- 0** Instructs the assembler to open the library data set, and supply the macro and copy code library input records to the exit in later PROCESS calls.

**Note:** A reason code of 4 indicates that the exit expects to receive END OF MEMBER calls.

A reason code of 16 indicates a REINIT call is required.

- 4** Indicates that the exit supplies the macro and copy code library records to the assembler in later READ calls. If you wish to provide the assembler with the values for the system variables &SYSLIB\_DSN, &SYSLIB\_MEMBER and &SYSLIB\_VOLUME, the user exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. The assembler also shows this information in the Diagnostic Cross Reference and Assembler Summary section of the listing, and includes it in the associated data file Library record.

**Note:** A reason code of 4 indicates that the exit expects to receive END OF MEMBER calls.

A reason code of 16 indicates a REINIT call is required.

- 8** Indicates that both the assembler and user exit supply the macro and copy code library records. On return from the exit, the assembler opens the library data set. When a macro or copy member is required, the assembler calls the exit with a FIND request. If the member is found by the exit, the exit supplies the records in later READ calls. If the exit cannot find the member, the assembler attempts to find the member in the library data set. If the assembler finds the member, the records are passed to the exit in later PROCESS calls.

**Note:** A reason code of 4 indicates that the exit expects to receive END OF MEMBER calls.

A reason code of 16 indicates a REINIT call is required.

- 16** Instructs the assembler to open the library data set, and make no further calls to the exit.

If you provide a character string in the *str2* suboption of the EXIT assembler option, the buffer pointer field points to the character string, and buffer length contains the length of the character string. The buffer length is set to zero if there is no character string.

## CLOSE

The assembler calls the exit with a request type of 2 (CLOSE) at the end of the assembly. The exit should close any data sets it opened and release any storage that it acquired.

## READ

The assembler calls the exit with a request type of 3 (READ) when the exit is supplying the library records, and after a successful FIND request. For copy members, the assembler calls the exit until the exit indicates the end-of-file. For macro definitions, the assembler calls the exit until it receives a MEND statement, or the exit indicates the end-of-file.

## LIBRARY exit processing

The exit can set the return code in the Exit Parameter List to one of the following:

- 0 The exit is supplying a record. The record must be placed in the area pointed to by the buffer pointer field. The record area is 80 characters in length.

The user exit should maintain the absolute record number and the relative record number. These fields are set to zero before the OPEN request. The assembler uses the relative record number in diagnostic messages when you specify the FLAG(RECORD) assembler option. If you specify the ADATA assembler option, the assembler includes both fields in the associated data file Source Analysis record.

**Note:** A reason code of 8 requests redrive of the exit.

- 16 Indicates to the assembler that there are no more records. This is equivalent to end-of-file processing for input members.

**Note:** A reason code of 8 requests redrive of the exit.

## PROCESS MACRO or PROCESS COPY

The assembler calls the exit with a request type of 5 (PROCESS MACRO) or 6 (PROCESS COPY) when the assembler is reading members from the library data set, and it has a record for the exit to process. The exit is also called with these request types when both the assembler and the exit are supplying library records (return code 8 from the OPEN call), and the assembler is supplying the record. The address of the record read is in the buffer pointer field, and the length is in the buffer length field. The record length is always 80.

The exit can set the return code in the Exit Parameter List to one of the following:

- 0 Indicates that the record has been accepted, and the assembler is to process it. The exit can modify the record before it returns control to the assembler. The user exit can also insert extra records in the library member by setting the reason code to 4. The assembler processes the current record and then calls the user exit with an empty buffer. The exit must place the record in the 80-byte area pointed to by the buffer pointer field. The exit can continue to supply additional records by setting the reason code to 4. The exit must keep track of when the assembler calls it with an empty buffer, and ensure that it resets the reason code to zero to resume normal processing.

**Note:** A reason code of 8 requests redrive of the exit.

- 4 Instructs the assembler to discard the current record.

**Note:** A reason code of 8 requests redrive of the exit.

- 16 Instructs the assembler to make no further calls to the exit. This will be disregarded by the assembler if the exit return code from the OPEN was 8.

Although the user exit can insert or discard records, the assembler maintains the absolute record number and relative record number.

If the options field is set to 1, the assembler has provided the exit with the current primary input data set information in the data set name, member name, and



volume serial fields of the exit-specific information block. The assembler updates this information when it reads the first record of each data set in a data set concatenation.

## FIND MACRO or FIND COPY

The assembler calls the exit with a request type of 7 (FIND MACRO) whenever the assembler cannot find an operation code and the exit issued a return code on OPEN of either 4 or 8. The member name field contains the operation code, and is the name of the macro definition that the assembler is searching for.

The assembler calls the exit with a request type of 8 (FIND COPY) whenever the assembler processes a COPY instruction and the exit issued a return code on OPEN of either 4 or 8. The member name field contains the name of the copy code member.

If the user exit is supplying the library records, the exit can set the return code in the Exit Parameter List to one of the following:

- 0 Indicates that the exit supplies the library records. The assembler calls the user exit with later READ calls to retrieve each record.

**Note:** A reason code of 8 requests redrive of the exit.

- 4 Indicates that the exit is not supplying the macro or copy member, and is equivalent to not finding the member in the library.

**Note:** A reason code of 8 requests redrive of the exit.

If both the assembler and the user exit are supplying the library records, the exit can set the return code in the Exit Parameter List to one of the following:

- 0 Indicates that the exit supplies the library records. The assembler calls the user exit with later READ calls to retrieve each record.

**Note:** A reason code of 8 requests redrive of the exit.

- 4 Indicates that the exit is not supplying the macro or copy member, and is equivalent to not finding the member in the library. On return from the exit, the assembler attempts to find the member in the library. If the assembler finds the member, it calls the user exit with later PROCESS MACRO or PROCESS COPY calls passing each record read from the library.

**Note:** A reason code of 8 requests redrive of the exit.

## System variables

If you wish to provide the assembler with the values for the system variables &SYSLIB\_DSN, &SYSLIB\_MEMBER, and &SYSLIB\_VOLUME, the user exit must set the return code to 0, the reason code to 4, and place the values in the data set name, member name, and volume serial fields of the exit-specific information block.

If the exit does not supply the data set information, the system variables are set to null, and the library data set details are not shown in the Diagnostic Cross Reference and Assembler Summary section of the listing, nor are they included in the ADATA Library record.

### Nesting COPY instructions and macro definitions

The assembler lets you code COPY instructions and macro call instructions in copy code members. It also lets you code COPY instructions in macro definitions. This type of coding is described as *nesting*.

If the exit is processing a member, and supplies a record to the assembler containing a COPY instruction, or a macro call instruction, the assembler calls the exit with a request type of FIND COPY or FIND MACRO, respectively. In this case, the exit needs to save the position in the currently active member before reading the new copy code or macro member. This enables the exit to resume processing the currently active member after it finishes with the new member.

The assembler indicates that it is processing a new (or nested) member by setting the options field to 3. When the assembler finishes processing the new member and resumes the previous (or outer) member, it issues a FIND call to the exit with the options field set to 2 indicating that the previous member is resumed. After the FIND call is complete, the assembler continues with PROCESS or READ calls to the exit for the previous member.

When the assembler calls the exit with a FIND COPY or FIND MACRO request, and the options field is set to 3, the exit should save the current member control information in a stack.

When the assembler calls the exit with a FIND COPY or FIND MACRO request, and the options field is set to 2, the exit should restore the previous member control information from the stack. The next READ request expects the next record from the previous member.

The assembler does not limit the number of levels of nesting.

There is a corresponding FIND (resume) request for every successful nested FIND request, except under the following situations:

- An END instruction is found while reading a copy code member. The END instruction causes the assembly to stop.
- When the assembler issues a PROCESS call, and provides the last record in a copy code member, and the record is a macro call. In this case there are no more copy records to resume reading.
- When a macro call (outer macro) inside a copy code member in turn issues a macro call (inner macro). In this case, the assembler processes the outer macro to completion, and then begins to generate the outer macro. During generation, the assembler begins to process the inner macro, without issuing a FIND (resume) request for the outer macro or copy code member. The assembler issues a FIND request for each nested macro call, with options set to 3. It does not issue a FIND request for the outer macro, with options set to 2, because the outer macro processing is complete.
- An error occurs during the assembly that prevents the member from being read completely.

If the FIND COPY or FIND MACRO is unsuccessful, the position in the currently active member should not be affected.

## END OF MEMBER

The assembler calls the exit with a request type of 9 (END OF MEMBER) whenever the reading of a macro or copy member is completed. For a macro, processing of a MEND statement indicates completion; for a copy member, an end of file condition indicates completion.

The END OF MEMBER call simplifies stack management required in coding a LIBRARY exit which contains READs and FINDs. The exit may use the information provided by this call in the handling of nested FINDs where there is usually, but not always, a corresponding resume FIND (options=2) for every nested FIND (options=3). For an example of how you can use END OF MEMBER calls to perform stack management, see page 136.

**Note:** A reason code of 8 requests redrive of the exit.

Table 17 summarizes the LIBRARY exit processing.

*Table 17. LIBRARY exit processing summary*

Request Value=Type	Exit Return Code	Action
1=OPEN	0	Assembler opens its library for input. If reason code=4, the assembler makes END OF MEMBER calls to the exit. If reason code=16, REINIT call required.
	4	Exit supplies library records. If reason code=4, the assembler makes END OF MEMBER calls to the exit. If reason code=16, REINIT call required.
	8	Both the assembler and the exit supply library records. The assembler opens its library. If reason code=4, the assembler makes END OF MEMBER calls to the exit. If reason code=16, REINIT call required.
	16	Assembler opens the library data set, and makes no further calls to the EXIT.
2=CLOSE	n/a	Exit should close any data sets it opened, and release any storage it acquired.
3=READ	0	Exit supplies record in buffer. Record with MEND statement indicates end of macro member.
	16	Exit indicates end-of-file for member.
5=PROCESS MACRO	0	Record accepted. Exit can modify record. If reason code=4, the assembler, after processing the current record, provides an empty buffer for the exit to provide additional record. If reason code=8, redrive requested. <sup>1</sup>
	4	Requests assembler to discard record. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the EXIT (disregarded if the EXIT return code from the OPEN is 8).

## LIBRARY exit processing

Table 17. LIBRARY exit processing summary (continued)

Request Value=Type	Exit Return Code	Action
6=PROCESS COPY	0	Record accepted. Exit can modify record. If reason code=4, the assembler, after processing the current record, provides an empty buffer for the exit to provide additional record. If reason code=8, redrive requested. <sup>1</sup>
	4	Requests assembler to discard record. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the EXIT (disregarded if the EXIT return code from the OPEN is 8).
7=FIND MACRO	0	Macro member found by exit; the exit supplies the records. If options=3, the exit should save the current member position. If options=2, the exit should restore the previous member position. If reason code=4, exit supplies data set information. If reason code=8, redrive requested. <sup>1</sup>
	4	Macro member not found by exit; the exit does not supply the records.
8=FIND COPY	0	Copy code member found by exit; the exit supplies the records. If options=3, the exit should save the current member position. If options=2, the exit should restore the previous member position. If reason code=4, exit supplies data set information. If reason code=8, redrive requested. <sup>1</sup>
	4	Copy code member not found by exit; the exit does not supply the records.
9=END OF MEMBER		Exit may use the information to perform stack management. If reason code=8, redrive requested. <sup>1</sup>
10=REINIT	0	Operation successful. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.

**Notes:**

1. When redrive is requested, the assembler issues any required error message and then recalls the exit with the same parameter list as before.

## LISTING exit processing

You can use the LISTING exit to override the effect of the LIST assembler option. The exit does this by indicating to the assembler that it opens the listing data set and does all listing output processing. Then, as each listing record is passed to the exit, the exit can decide whether to print the record, and where it writes the record. For instance, the exit can write the listing records to a different data set than the assembler would normally write them.

The LISTING exit is not called if you specify the NOLIST assembler option. If you wish to process the listing records in the exit but you do not want the assembler to write the records to the normal output data set, you can do one of these:

- Instruct the assembler to discard the listing records by setting the exit return code.
- Suppress the listing output by doing this:
  - z/OS** Provide a //SYSPRINT DD DUMMY JCL statement.
  - CMS** Issue a FILEDEF SYSPRINT DUMMY command.
  - z/VSE** Assign the SYSLST to IGN.
- Instruct the exit to issue an OPEN return code of 4.

The sections of the listing that are passed to the exit depend on the assembler options you specify. For instance, if you specify the NORLD option, then no Relocation Dictionary listing records are passed to the exit.

#### z/VM and z/OS

Although the assembler can write to a listing data set with a record format of variable-length, the exit is always presented with fixed-length records.

End of z/VM and z/OS

The assembler calls the LISTING exit with the following request types:

## OPEN

The assembler calls the exit with a request type of 1 (OPEN) at the start of the assembly.

The exit may set the return code in the Exit Parameter List to one of the following:

- 0** Instructs the assembler to open the listing data set, and supply the listing output records to the exit in later PROCESS calls.

The exit can set the record length for the listing data set by setting the reason code to 4 and the buffer length field.

**Note:** A reason code of 16 indicates a REINIT call is required.

#### z/VM and z/OS

The buffer length field can be set to any value from 121 to 255. If the listing data set has a variable-length record format, the LRECL assigned is 4 bytes greater than the value the exit returns. If the value is less than 121 or greater than 255, the assembler issues message ASMA402W and does not call the exit for any further processing.

End of z/VM and z/OS

#### z/VSE

The buffer length field can be set to any value from 121 to 133. If the value is less than 121 or greater than 133, the assembler issues message ASMA402W and does not call the exit for any further processing.

## LISTING exit processing

If you assign SYSLST to a disk data set in your JCL, the record length must be 121.

End of z/VSE

- 4 Indicates that the exit writes the listing records in later WRITE calls. If you wish to provide the assembler with the values for the system variables &SYSPRINT\_DSN, &SYSPRINT\_MEMBER, and &SYSPRINT\_VOLUME, the exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. The assembler also shows this information in the Diagnostic Cross Reference and Assembler Summary section of the listing, and includes it in the associated data file Output File Information record.

**Note:** A reason code of 16 indicates a REINIT call is required.

- 16 Instructs the assembler to open the listing data set, and make no further calls to the exit.

The assembler sets the linecount field to the value of the LINECOUNT assembler option. This value is the number of lines per page in the listing. The exit can change the line count to a value of 0, or any value from 10 to 32767. "LINECOUNT" on page 61 describes the LINECOUNT assembler option.

If you provide a character string in the *str3* suboption of the EXIT assembler option, the buffer pointer field points to the character string, and buffer length contains the length of the character string. The buffer length is set to zero if there is no character string.

## CLOSE

The assembler calls the exit with a request type of 2 (CLOSE) at the end of the assembly. The exit should close any data sets it opened and release any storage that it acquired.

## WRITE

The assembler calls the exit with a request type of 4 (WRITE) when the exit is writing the listing records. The buffer pointer field points to the listing record, and the buffer length contains the length of the record.

**Note:** A reason code of 8 requests redrive of the exit.

z/VM and z/OS

Depending on the setting of the ASA assembler option, the record has either an American National Standard or a machine printer control character at the start of the record.

End of z/VM and z/OS

The options field contains a value that represents the type of listing record that is passed. The listing record types, and their corresponding options values, are shown on page 93.

The user exit should maintain the absolute record number and the relative record number. These fields are set to zero before the OPEN request. The assembler uses

the relative record number and the linecount value to determine when to start a new page in the assembler listing. A new page is started when the relative record number exceeds the line count.

## PROCESS

The assembler calls the exit with a request type of 5 (PROCESS) when the assembler is writing the listing records, and it has a record for the exit to process. The address of the record is in the buffer pointer field, and the length is in the buffer length field.

z/VM and z/OS

The record has either an American National Standard or a machine printer control character at the start of the record depending on the setting of the ASA assembler option.

End of z/VM and z/OS

The options field contains a value that represents the type of listing record that is passed. The listing record types, and their corresponding options values, are shown on page 93.

The exit can set the return code in the Exit Parameter List to one of the following:

- 0 Indicates that the record has been accepted, and the assembler is to write it to the listing data set. The exit may modify the record before it returns control to the assembler. The user exit may also insert extra records in the listing by setting the reason code to 4. The assembler writes the current record and then calls the user exit with an empty buffer. The exit must place the additional listing record in the area pointed to by the buffer pointer field. The exit can continue to supply additional records by setting the reason code to 4. The exit must keep track of when the assembler calls it with an empty buffer, and ensure that it resets the reason code to zero to resume normal processing.

**Note:** A reason code of 8 requests redrive of the exit.

z/VM and z/OS

The exit must also ensure that a valid printer control character is placed in the first character of the record. The printer control character may be either American National Standard or machine. The exit can check the DCB, pointed to by the DCB pointer field in the Exit Parameter List, to find out which printer control character to use.

End of z/VM and z/OS

z/VSE

The exit must also ensure that a valid American National Standard printer control character is placed in the first character of the record.

End of z/VSE

- 4 Instructs the assembler to discard the listing record.

## LISTING exit processing

**Note:** A reason code of 8 requests redrive of the exit.

**16** Instructs the assembler to make no further calls to the exit.

Although the user exit can insert or discard records, the assembler maintains the absolute record number and relative record number.

Table 18 summarizes the LISTING exit processing.

Table 18. LISTING exit processing summary

Request Value=Type	Exit Return Code	Action
1=OPEN	0	Assembler opens listing data set. If reason code=4, exit supplies listing line length. If reason code=16, REINIT call required.
	4	Exit writes listing records. If reason code=4, exit supplies data set information. If reason code=16, REINIT call required.
	16	Assembler opens listing data set, and makes no further calls to the exit.
2=CLOSE	n/a	Exit should close any data sets it opened, and release any storage it acquired.
4=WRITE	0	Exit writes record. If reason code=8, redrive requested. <sup>1</sup>
5=PROCESS	0	Record accepted. Exit may modify record. If reason code=4, the assembler, after processing the current record, provides an empty buffer for the exit to provide additional record. If reason code=8, redrive requested. <sup>1</sup>
	4	Requests assembler to discard record. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.
10=REINIT	0	Operation successful. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.

### Notes:

1. When redrive is requested, the assembler issues any required error message and then recalls the exit with the same parameter list as before.

## OBJECT (z/OS and CMS) and PUNCH exit processing

When you specify the OBJEXIT suboption of the EXIT assembler option, the assembler calls either the PUNCH user exit or the OBJECT user exit, or both, as follows:

### z/VM and z/OS

- If you specify the OBJECT assembler option, the assembler calls the OBJECT user exit.



## OBJECT (z/OS and CMS) and PUNCH exit processing

- If you specify the OBJECT and the DECK assembler options, the assembler calls the user exit as a PUNCH exit, and then as an OBJECT exit.
- If you specify the DECK assembler option, the assembler calls the PUNCH user exit.

End of z/VM and z/OS

You can use the exit to override the effect of the DECK or OBJECT assembler options. The exit does this by indicating to the assembler that it opens the output data set and does all the output processing. Then, as each object record is passed to the exit, the exit can decide whether to write the record, and where to write the record. For instance, the exit can write the records to a different data set than the assembler would normally write them.

z/VM and z/OS

The exit is not called if you specify the NODECK and NOOBJECT assembler options.

End of z/VM and z/OS

z/VSE

The exit is not called if you specify the NODECK assembler option.

End of z/VSE

If you wish to process the object records in the exit, but you do not want the assembler to write the records to the normal output data set, you can do one of these:

- Instruct the assembler to discard the records by setting the exit return code.
- Suppress the object output by doing this:
  - z/OS** Provide a //SYSLIN DD DUMMY JCL statement, and a //SYSPUNCH DD DUMMY JCL statement.
  - CMS** Issue a FILEDEF SYSLIN DUMMY command, and a FILEDEF SYSPUNCH DUMMY command.
  - z/VSE** Assign SYSPCH to IGN.
- Instruct the exit to issue an OPEN return code of 4.

The assembler calls the OBJECT and PUNCH exit with the following request types:

### OPEN

The assembler calls the exit with a request type of 1 (OPEN) at the start of the assembly. The exit type field indicates which exit is being called. The OBJECT exit is type 5, and the PUNCH exit is type 4.

The exit can set the return code in the Exit Parameter List to one of the following:

- 0** Instructs the assembler to open the object data set, and supply the object records to the exit in later PROCESS calls.

**Note:** A reason code of 16 indicates a REINIT call is required.

- 4** Indicates that the exit writes the object records in later WRITE calls. If you wish to provide the assembler with the values for the system variables &SYSLIN\_DSN, &SYSLIN\_MEMBER, and &SYSLIN\_VOLUME, then

## OBJECT (z/OS and CMS) and PUNCH exit processing

during the OPEN call for the OBJECT exit, the exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. If you wish to provide the assembler with the values for the system variables &SYSPUNCH\_DSN, &SYSPUNCH\_MEMBER, and &SYSPUNCH\_VOLUME, then during the OPEN call for the PUNCH exit, the exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. The assembler also shows the information for both object and punch data sets in the Diagnostic Cross Reference and Assembler Summary section of the listing, and includes it in the associated data file Output File Information record.

**Note:** A reason code of 16 indicates a REINIT call is required.

- 16      Instructs the assembler to open the object data set and make no further calls to the exit.

If you provide a character string in the *str4* suboption of the EXIT assembler option, the buffer pointer field points to the character string, and the buffer length contains the length of the character string. The buffer length is set to zero if there is no character string.

**Note:** If both OBJECT and DECK are specified (so that the exit is called twice), the optional character string specified in the PARM string is passed each time.

## CLOSE

The assembler calls the exit with a request type of 2 (CLOSE) at the end of the assembly. The exit should close any data sets it opened and release any storage that it acquired.

## WRITE

The assembler calls the exit with a request type of 4 (WRITE) when the exit is writing the object records. The buffer pointer field points to the object record, and the buffer length contains the length of the record.

**Note:** A reason code of 8 requests redrive of the exit.

### z/VM and z/OS

The record length is always 80 bytes when you specify the NOGOFF assembler option. If you specify the GOFF assembler option, the record length is 80 bytes for fixed-length output or up to 8212 bytes for variable-length output. The record length for variable-length records does not include the 4-byte length of the record descriptor word (RDW), and the buffer pointer field points at the object data, not the RDW.

End of z/VM and z/OS

### z/VSE

The record length is always 80 bytes.

End of z/VSE

The user exit should maintain the absolute record number and the relative record number. These fields are set to zero before the OPEN request.

### PROCESS

The assembler calls the exit with a request type of 5 (PROCESS) when the assembler is writing the object records, and it has a record for the exit to process. The address of the record is in the buffer pointer field, and the length is in the buffer length field.

#### z/VM and z/OS

The record length is always 80 bytes when you specify the NOXOBJECT assembler option. If you specify the XOBJECT assembler option, the record length is 80 bytes for fixed-length output or up to 8212 bytes for variable-length output. The record length for variable-length records does not include the 4-byte length of the record descriptor word (RDW), and the buffer pointer field points at the object data, not the RDW.

End of z/VM and z/OS

#### z/VSE

The record length is always 80 bytes.

End of z/VSE

The exit can set the return code in the Exit Parameter List to one of the following:

- 0 Indicates that the record has been accepted, and the assembler is to write it to the object data set. The exit can modify the record before it returns control to the assembler. The user exit can also insert extra records in the object data set by setting the reason code to 4. The assembler writes the current record and then calls the user exit with an empty buffer. The exit must place the additional object record in the area pointed to by the buffer pointer field. The exit can continue to supply additional records by setting the reason code to 4. The exit must keep track of when the assembler calls it with an empty buffer, and ensure that it resets the reason code to zero to resume normal processing.

**Note:** A reason code of 8 requests redrive of the exit.

- 4 Instructs the assembler to discard the record.

**Note:** A reason code of 8 requests redrive of the exit.

- 16 Instructs the assembler to make no further calls to the exit.

Although the user exit can insert or discard records, the assembler maintains the absolute record number and relative record number.

## OBJECT (z/OS and CMS) and PUNCH exit processing

Table 19 summarizes the OBJECT and PUNCH exit processing.

Table 19. OBJECT and PUNCH exit processing summary

Request Value=Type	Exit Return Code	Action
1=OPEN	0	Assembler opens object data set. If reason code=16, REINIT call required.
	4	Exit writes object records. If reason code=4, exit supplies data set information. If reason code=16, REINIT call required.
	16	Assembler opens object data set, and makes no further calls to the exit.
2=CLOSE	n/a	Exit should close any data sets it opened, and release any storage it acquired.
4=WRITE	0	Exit writes record. If reason code=8, redrive requested. <sup>1</sup>
5=PROCESS	0	Record accepted. Exit can modify record. If reason code=4, the assembler, after processing the current record, provides an empty buffer for the exit to provide additional record. If reason code=8, redrive requested. <sup>1</sup>
	4	Requests assembler to discard record. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.
10=REINIT	0	Operation successful. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.

### Notes:

1. When redrive is requested, the assembler issues any required error message and then recalls the exit with the same parameter list as before.

## ADATA exit processing

When you specify the ADEXIT suboption of the EXIT assembler option, the assembler calls the ADATA user exit if you also specify the ADATA assembler option.

The ADATA exit is not called if you specify the NOADATA assembler option. If you wish to process the associated data records in the exit, but you do not want the assembler to write the records to the normal output data set, you can do one of these:

- Instruct the assembler to discard the associated data records by setting the exit return code.
- Suppress the associated data output by doing this:
  - z/OS** Provide a //SYSADATA DD DUMMY JCL statement.
  - CMS** Issue a FILEDEF SYSADATA DUMMY command.
  - z/VSE** Assign SYSADAT to IGN.

The assembler calls the ADATA exit with the following request types:

## OPEN

The assembler calls the exit with a request type of 1 (OPEN) at the start of the assembly.

If you provide a character string in the *str5* suboption of the EXIT assembler option, the buffer pointer field points to the character string, and the buffer length contains the length of the character string. The buffer length is set to zero if there is no character string.

The exit can set the return code in the Exit Parameter List to one of the following:

- 0 Instructs the assembler to open the associated data data set, and supply the associated data records to the exit in later PROCESS calls.

**Note:** A reason code of 8 indicates that the exit intends to discard both type X'0002' and X'0090' records that may be presented to it during the assembly.

This reason code is used by the assembler when building the assembler summary section of the listing. To calculate accurate associated data record counts the assembler must be aware of any future discards of the final two records to be written; the statistics record and the end record.

A reason code of 16 indicates a REINIT call is required.

- 4 Indicates that the exit writes the associated data records in later WRITE calls. If you wish to provide the assembler with the values for the system variables &SYSADATA\_DSN, &SYSADATA\_MEMBER, and &SYSADATA\_VOLUME, the exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. The assembler also shows this information in the Diagnostic Cross Reference and Assembler Summary section of the listing, and includes it in the associated data file Output File Information record.

**Note:** A reason code of 8 indicates that the exit intends to discard both type X'0002' and X'0090' records that may be presented to it during the assembly.

This reason code is used by the assembler when building the assembler summary section of the listing. To calculate accurate associated data record counts the assembler must be aware of any future discards of the final two records to be written; the statistics record and the end record.

A reason code of 16 indicates a REINIT call is required.

- 16 Instructs the assembler to open the ADATA data set and make no further calls to the exit.

## CLOSE

The assembler calls the exit with a request type of 2 (CLOSE) at the end of the assembly. The exit should close any data sets it opened and release any storage that it acquired.

### WRITE

The assembler calls the exit with a request type of 4 (WRITE) when the exit is writing the associated data records. The buffer pointer field points to the associated data record, and the buffer length contains the length of the record. The record length for variable-length records does not include the 4-byte length of the record descriptor word (RDW), and the buffer pointer field points at the associated data header, not the RDW.

**Note:** A reason code of 8 requests redrive of the exit.

The user exit should maintain the absolute record number and the relative record number. These fields are set to zero before the OPEN request.

### PROCESS

The assembler calls the exit with a request type of 5 (PROCESS) when the assembler is writing the associated data records, and it has a record for the exit to process. The address of the record read is in the buffer pointer field, and the length is in the buffer length field. The record length for variable-length records does not include the 4-byte length of the record descriptor word (RDW), and the buffer pointer field points at the associated data header, not the RDW.

The exit can set the return code in the Exit Parameter List to one of the following:

- 0 Indicates that the record has been accepted, and the assembler is to write it to the associated data data set. The exit can modify the record before it returns control to the assembler. The user exit can also insert extra records in the associated data data set by setting the reason code to 4. The assembler writes the current record and then calls the user exit with an empty buffer. The exit must place the additional associated data record in the area pointed to by the buffer pointer field. The exit can continue to supply additional records by setting the reason code to 4. The exit must keep track of when the assembler calls it with an empty buffer, and ensure that it resets the reason code to zero to resume normal processing.

**Note:** A reason code of 8 requests redrive of the exit.

- 4 Instructs the assembler to discard the record.

**Note:** A reason code of 8 requests redrive of the exit.

- 16 Instructs the assembler to make no further calls to the exit.

Although the user exit can insert or discard records, the assembler maintains the absolute record number and relative record number.

Table 20 summarizes the ADATA exit processing.

*Table 20. ADATA exit processing summary*

<b>Request Value=Type</b>	<b>Exit Return Code</b>	<b>Action</b>
1=OPEN	0	Assembler opens associated data data set. If reason code=8, exit intends to discard both X'0002' and X'0090' record types. If reason code=16, REINIT call required.
	4	Exit writes associated data records. If reason code=4, exit supplies data set information. If reason code=8, exit intends to discard both X'0002' and X'0090' record types. If reason code=16, REINIT call required.
	16	Assembler opens associated data data set, and makes no further calls to the exit.
2=CLOSE	n/a	Exit should close any data sets it opened, and release any storage it acquired.
4=WRITE	0	Exit writes record. If reason code=8, redrive requested. <sup>1</sup>
5=PROCESS	0	Record accepted. Exit can modify record. If reason code=4, the assembler, after processing the current record, provides an empty buffer for the exit to provide additional record. If reason code=8, redrive requested. <sup>1</sup>
	4	Requests assembler to discard record. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.
10=REINIT	0	Operation successful. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.

**Notes:**

1. When redrive is requested, the assembler issues any required error message and then recalls the exit with the same parameter list as before.

## TERM exit processing

You can use the TERM exit to override the effect of the TERM assembler option. The exit does this by indicating to the assembler that it opens the terminal data set and does all terminal output processing. Then, as each terminal record is passed to the exit, the exit can decide whether to write the record, and where to write the record. For instance, the exit can write the terminal records to a different data set to which the assembler would normally write them.

The TERMINAL exit is not called if you specify the NOTERM assembler option. If you wish to process the terminal records in the exit, but you do not want the assembler to write the records to the normal output data set, you can do one of these:

- Instruct the assembler to discard the terminal records by setting the exit return code.
- Suppress the terminal output by doing this:
  - z/OS** Provide a //SYSTEM DD DUMMY JCL statement.
  - CMS** Issue a FILEDEF SYSTEM DUMMY command.

## TERM exit processing

**z/VSE** Assign SYSTERM to IGN.

- Instruct the exit to issue an OPEN return code of 4.

The assembler calls the TERMINAL exit with the following request types:

### OPEN

The assembler calls the exit with a request type of 1 (OPEN) at the start of the assembly.

The exit may set the return code in the Exit Parameter List to one of the following:

- 0        Instructs the assembler to open the terminal data set, and supply the terminal output records to the exit in later PROCESS calls.

The exit can set the record length for the terminal data set by setting the reason code to 4 and the buffer length field. The buffer length field can be set to any value from 1 to 255 on z/OS and CMS, or from 1 to 125 on z/VSE. If the value is zero or greater than 255 on z/OS and CMS, or zero or greater than 125 on z/VSE, the assembler issues message ASMA404W and does not call the exit for any further processing.

**Note:** A reason code of 16 indicates a REINIT call is required.

- 4        Indicates that the exit writes the terminal records in later WRITE calls. If you wish to provide the assembler with the values for the system variables &SYSTERM\_DSN, &SYSTERM\_MEMBER, and &SYSTERM\_VOLUME, the exit must set the reason code to 4 and place the values in the data set name, member name, and volume serial fields of the exit-specific information block. The assembler also shows this information in the Diagnostic Cross Reference and Assembler Summary section of the listing, and includes it in the associated data file Output File Information record.

**Note:** A reason code of 16 indicates a REINIT call is required.

- 16       Instructs the assembler to open the terminal data set and make no further calls to the exit.

If you provide a character string in the *str6* suboption of the EXIT assembler option, the buffer pointer field points to the character string, and the buffer length contains the length of the character string. The buffer length is set to zero if there is no character string.

### CLOSE

The assembler calls the exit with a request type of 2 (CLOSE) at the end of the assembly. The exit should close any data sets it opened and release any storage that it acquired.

### WRITE

The assembler calls the exit with a request type of 4 (WRITE) when the exit is writing the terminal records. The buffer pointer field points to the terminal record, and the buffer length contains the length of the record.

The user exit should maintain the absolute record number and the relative record number. These fields are set to zero before the OPEN request.

**Note:** A reason code of 8 requests redrive of the exit.



## PROCESS

The assembler calls the exit with a request type of 5 (PROCESS) when the assembler is writing the terminal records, and it has a record for the exit to process. The address of the record is in the buffer pointer field, and the length is in the buffer length field.

The exit can set the return code in the Exit Parameter List to one of the following:

- 0 Indicates that the record has been accepted, and the assembler is to write it to the terminal data set. The exit may modify the record before it returns control to the assembler. The user exit may also insert extra records in the terminal by setting the reason code to 4. The assembler writes the current record and then calls the user exit with an empty buffer. The exit must place the additional terminal record in the area pointed to by the buffer pointer field. The exit can continue to supply additional records by setting the reason code to 4. The exit must keep track of when the assembler calls it with an empty buffer, and ensure that it resets the reason code to zero to resume normal processing.

**Note:** A reason code of 8 requests redrive of the exit.

- 4 Instructs the assembler to discard the terminal record.

**Note:** A reason code of 8 requests redrive of the exit.

- 16 Instructs the assembler to make no further calls to the exit.

Although the user exit can insert or discard records, the assembler maintains the absolute record number and relative record number.

Table 21 summarizes the TERM exit processing.

*Table 21. TERM exit processing summary*

Request Value=Type	Exit Return Code	Action
1=OPEN	0	Assembler opens terminal data set. If reason code=4, exit supplies listing line length. If reason code=16, REINIT call required.
	4	Exit writes terminal records. If reason code=4, exit supplies system variable symbols. If reason code=16, REINIT call required.
	16	Assembler opens terminal data set, and makes no further calls to the exit.
2=CLOSE	n/a	Exit should close any data sets it opened, and release any storage it acquired.
4=WRITE	0	Exit writes record. If reason code=8, redrive requested. <sup>1</sup>

## TERM exit processing

Table 21. TERM exit processing summary (continued)

Request Value=Type	Exit Return Code	Action
5=PROCESS	0	Record accepted. Exit can modify record. If reason code=4, the assembler, after processing the current record, provides an empty buffer for the exit to provide additional record. If reason code=8, redrive requested. <sup>1</sup>
	4	Requests assembler to discard record. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.
10=REINIT	0	Operation successful. If reason code=8, redrive requested. <sup>1</sup>
	16	Assembler makes no further calls to the exit.

### Notes:

1. When redrive is requested, the assembler issues any required error message and then recalls the exit with the same parameter list as before.

## Sample user exits

Three sample exits are provided with High Level Assembler. They are described under:

- Appendix I, "Sample ADATA user exits (z/OS and CMS)," on page 391
- Appendix J, "Sample LISTING user exit (z/OS and CMS)," on page 403
- Appendix K, "Sample SOURCE user exit (z/OS and CMS)," on page 405

## User exit coding example

Figure 26 on page 128 shows how to code a user exit. The exit is called "MYEXIT". It uses all user exit types and all request types. It uses the field AXPUSER to anchor the storage it has acquired to make it reenterable.

This user exit is not supplied with High Level Assembler. This exit is written for z/OS and CMS only.

The user exit does not show examples of how to open, read, write, or close a data set when it is responsible for opening the data set. Instead, it provides source records from its own storage, and writes output records to the operator using the WTO macro.

The user exit can be invoked as the following exit types.

**SOURCE Exit—INEXIT:** If you specify EXIT(INEXIT(MYEXIT)), the exit allows the assembler to open the input data set. The exit issues a WTO for each record read from the input data set.

If you specify EXIT(INEXIT(MYEXIT(EXIT))), the exit opens the input data set. It passes the following records to the assembler:

```
SMALL  TITLE 'Test the assembler exits'
        MACRO
        LITTLE
        BSM  0,14  Return
        MEND
        START
```

```

OUTER
LITTLE
REPRO
This is to be written to the punch data set
COPY TINY
END

```

**LIBRARY Exit—LIBEXIT:** If you specify EXIT(LIBEXIT(MYEXIT)), the exit allows the assembler to open the library data set. The exit issues a WTO for each record read from the library data set.

If you specify EXIT(LIBEXIT(MYEXIT(EXIT))), the exit opens the library data set. It passes the records for the following macros and COPY members to the assembler:

- Macro OUTER
- Macro INNER
- COPY member TINY
- COPY member TINY1

If you specify EXIT(LIBEXIT(MYEXIT(BOTH))), the exit and the assembler opens the library data sets. The exit passes the records for the following macros and COPY members to the assembler:

- Macro OUTER
- Macro INNER
- COPY member TINY
- COPY member TINY1

**LISTING Exit—PRTEXIT:** If you specify EXIT(PRTEXIT(MYEXIT)), the exit allows the assembler to open the listing data set. The exit issues a WTO for the first 80 characters of each listing record.

If you specify EXIT(PRTEXIT(MYEXIT(EXIT))), the exit opens the listing data set. The exit issues a WTO for the first 80 characters of each listing record passed to the exit.

## OBJECT and PUNCH exit—OBJEXIT

If you specify EXIT(OBJEXIT(MYEXIT)), the exit allows the assembler to open the object and punch data sets. The exit issues a WTO for each object record written to the object and punch data set.

If you specify EXIT(OBJEXIT(MYEXIT(EXIT))), the exit opens the object and punch data set. The exit issues a WTO for each object record passed to the exit.

## ADATA Exit—ADEXIT

If you specify EXIT(ADEXIT(MYEXIT)), the exit allows the assembler to open the associated data data set. The exit issues a WTO for the first 80 characters of each associated data record.

If you specify EXIT(ADEXIT(MYEXIT(EXIT))), the exit opens the associated data data set. The exit issues a WTO for the first 80 characters of each associated data record passed to the exit.

## TERM exit—TRMEXIT

If you specify EXIT(TRMEXIT(MYEXIT)), the exit allows the assembler to open the terminal data set. The exit issues a WTO for the first 68 characters of each terminal record.

## User exit coding example

If you specify EXIT(TRMEXIT(MYEXIT(EXIT))), the exit opens the terminal data set. The exit issues a WTO for the first 68 characters of each terminal record passed to the exit.

---

```
MYEXIT  TITLE '- EXAMPLE OF A USER EXIT'
*****
*                                                                 *
* This sample user exit demonstrates how to code a user exit.    *
* It has code to demonstrate the use of SOURCE, LIBRARY, LISTING, *
* PUNCH, OBJECT, ADATA and TERM exits.                          *
*                                                                 *
* This user exit uses the field AXPUSER to anchor the storage it has *
* acquired to make it reenterable. If the user exit does not need to *
* be reenterable, this code is not required.                     *
*                                                                 *
* REGISTER USAGE:                                              *
*   R0 - WORK                                                  *
*   R1 - WORK                                                  *
*   R2 - WORK                                                  *
*   R3 - WORK                                                  *
*   R4 - WORK                                                  *
*   R5 - POINTER TO DCB (z/OS/CMS) ONLY                        *
*   R6 - POINTER TO SOURCE INFORMATION                         *
*   R7 - POINTER TO ERROR BUFFER                              *
*   R8 - POINTER TO BUFFER                                    *
*   R9 - POINTER TO REQUEST INFORMATION                       *
*   R10 - POINTER TO ORIGINAL PASSED PARAMETER                *
*   R11 - NOT USED.                                           *
*   R12 - PROGRAM SECTION BASE REGISTER                      *
*   R13 - SAVEAREA AND DYNAMIC STORAGE AREA                  *
*   R14 - RETURN ADDRESS OF CALLING MODULE                   *
*   R15 - ENTRY POINT OF CALLED MODULE                       *
*                                                                 *
*****
      PRINT NOGEN
      EJECT
```

---

Figure 26. Example of a user exit (Part 1 of 17)

```

*****
* MYEXIT  Entry                                     *
* - Save the registers.                             *
* - Acquire the dynamic storage on the first entry and save the *
*   address in AXPUSER.                             *
* - Chain the save areas using the forward and backward pointers. *
* - Address the data areas passed.                   *
* - Process the required exit according to the 'Exit type' passed. *
*****
MYEXIT  CSECT
        STM  R14,R12,12(R13)      Save registers
        LR   R12,R15              Set up first base register
        USING MYEXIT,R12,R11
        LA   R11,2048(,R12)
        LA   R11,2048(,R11)      Set up second base register
        LR   PARMREG,R1           Save parameter list address
        USING AXPXITP,PARMREG
        L    REQREG,AXPRIP       Get address of exit parm list
        USING AXPRIL,REQREG
        ICM  R1,B'1111',AXPUSER  Get address of user area
        BNZ  CHAIN               Yes, use area
        LA   0,WORKLEN            Otherwise, get length
        GETMAIN R,LV=(0)          and getmain storage
        ST   R1,AXPUSER           Save it for later
        XC   0(WORKLEN,R1),0(R1)  Clear area
CHAIN    DS   0H
        ST   R13,4(R1)            Save previous pointer
        ST   R1,8(R13)            Save next pointer
        LR   R13,R1              Set savearea/workarea address
        USING WORKAREA,R13
        SPACE 1
        L    BUFREG,AXPBUF       Get address of buffer
        USING BUFF,BUFREG
        L    ERRREG,AXPERRP      Get address of error buffer
        USING ERRBUFF,ERRREG
        L    SRCREG,AXPSIP       Get address of source info
        USING AXPSIL,SRCREG
        L    DCBREG,AXPDCBP      Get address of DCB
        USING IHADCB,DCBREG
        SPACE 1
        XC   AXPRETC,AXPRETC     Zero the return code
        L    R15,AXPTYPE         Load the exit type value (1-7)
        BCTR R15,0               Decrement by 1
        SLL  R15,1               Multiply by 2
        LH   R15,EXITADDR(R15)   Index into address list
        AR   R15,R12             Calculate the address
        BR   R15                 Branch to applicable routine
        SPACE 1
EXITADDR DC  Y(SOURCE-MYEXIT)
        DC  Y(LIBRARY-MYEXIT)
        DC  Y(LISTING-MYEXIT)
        DC  Y(PUNCH-MYEXIT)
        DC  Y(OBJECT-MYEXIT)
        DC  Y(ADATA-MYEXIT)
        DC  Y(TERM-MYEXIT)
        DC  Y(*-*)
EJECT

```

Figure 26. Example of a user exit (Part 2 of 17)

## User exit coding example

```
*****
* MYEXIT  Exit1                                     *
* - Restore the callers register 13                 *
* - Restore the registers and set the register 15 to zero. *
* - Return to the caller.                           *
*****
EXIT1  DS    0H
      MVC    LASTOP,AXPRTYP+3      Save last operation code
      L      R13,4(,R13)          Unchain save areas
EXIT2  DS    0H
      LM     R14,R12,12(R13)      Restore callers registers
      LA     R15,0                Set the return code
      BSM    R0,R14              Return to caller
      SPACE 1
*****
* MYEXIT  - Free storage                           *
* - Called on a CLOSE request.                     *
* - Free the storage acquired and zero AXPUSER.    *
* - Go to EXIT (after R13 is restored)             *
*****
FREESTOR DS    0H
        XC     AXPUSER,AXPUSER    Zero User field
        LA     0,WORKLEN          Length of area to free
        LR     R1,R13            Address of area to free
        L      R13,4(,R13)       Restore callers register 13
        FREEMAIN R,A=(1),LV=(0)  Free the storage acquired
        B      EXIT2
        SPACE 1
*****
* MYEXIT  - Logic error                           *
* - If an error occurred, set up the error message in the buffer *
*   and length in AXPERRL. Set the severity code. *
* - Set the return code to 20.                     *
* - Return to the caller.                           *
*****
LOGICERR DS    0H
        MVC    AXPRETCL=A(AXPCBAD) Severe error occurred
        MVC    ERRBUFF(ERRMSG),ERRMSG Set up error message
        MVC    AXPERRL=A(ERRMSG)   Set up error message length
        MVC    AXPSEVC=A(20)       Set up error message severity
        B      EXIT1
        EJECT
*****
* SOURCE EXIT                                     *
* - Process required request type                 *
*****
SOURCE  DS    0H
        L      R15,AXPRTYP        Get the request type value (1-5)
        BCTR   R15,0              Decrement by 1
        SLL    R15,1              Multiply by 2
        LH     R15,SOURCE_ADDR(R15) Index into Address list
        AR     R15,R12            Calculate the address
        BR     R15               Branch to applicable routine
SOURCE_ADDR DC Y(SOURCE_OPEN-MYEXIT)
           DC Y(SOURCE_CLOSE-MYEXIT)
           DC Y(SOURCE_READ-MYEXIT)
           DC Y(SOURCE_WRITE-MYEXIT)
           DC Y(SOURCE_PROCESS-MYEXIT)
           DC Y(*-*)
           SPACE 1
```

Figure 26. Example of a user exit (Part 3 of 17)

```

*****
* SOURCE EXIT - Process OPEN request                                     *
* - Pick up character string if it is supplied.                         *
* - Set return code indicating whether the assembler or user exit      *
*   will open the primary input data set.                             *
* - Open data set if required.                                         *
*****
SOURCE_OPEN    DS    0H
              MVI    OPENPARM,C' '          Clear open parm
              MVC    OPENPARM+1(L'OPENPARM-1),OPENPARM
              L      R1,AXPBUFL             Get the Buffer length
              LTR    R1,R1                  Is string length zero?
              BZ     SOURCE_NOSTR           Yes, no string passed
              BCTR   R1,0                    Decrement for execute
              EX     R1,UPPERSTR             Move and uppercase string
SOURCE_NOSTR   DS    0H
              CLC    OPENPARM(8),=CL8'EXIT' Will user exit read input?
              BE     SOURCE_OPEN_EXIT      Yes
              MVC    AXPRETCL,=A(0)        assembler to read primary input
              B      EXIT1                  Return
SOURCE_OPEN_EXIT DS  0H
              OI     OPENFLAG,EXIT         Set flag
              MVC    AXPRETCL,=A(AXPCOPN)  User exit to read primary input
              LA     R1,SRC1                Address first source record
              ST     R1,CURR_PTR            Set up pointer
              B      EXIT1                  Return
              SPACE 1
*****
* SOURCE EXIT - Process CLOSE request                                   *
* - Close data set if required.                                         *
* - Free storage and return.                                           *
*****
SOURCE_CLOSE   DS    0H
              B      FREESTOR
              SPACE 1

```

Figure 26. Example of a user exit (Part 4 of 17)

## User exit coding example

```
*****
* SOURCE EXIT - Process READ request                                     *
* - Provide source information on first read.                           *
* - Read primary input record and place in buffer.                     *
* - Set return code to 16 at end of file.                               *
*****
SOURCE_READ      DS      0H
                CLI      LASTOP,AXPROPN      Was last operation OPEN?
                BNE      SOURCE_READ2
                MVC      AXPMEMN,=CL255'Member'
                MVC      AXPMEMT,=CL255'None'
                MVC      AXPDNS,=CL255'INPUT.data set.NAME'
                MVC      AXPVOL,=CL255'VOL001'
                MVC      AXPREAD,=A(AXPEISA)  Indicate source info available
                XC      AXPRELREC,AXPRELREC    Set Relative Record No. to 0
                XC      AXPABSREC,AXPABSREC    Set Absolute Record No. to 0
SOURCE_READ2     DS      0H
                L        R1,CURR_PTR          Get record address
                CLI      0(R1),X'FF'         Is it EOF?
                BE       SOURCE_EOF          Yes, set return code
                MVC      0(80,BUFREG),0(R1)
                LA       R1,80(,R1)
                ST       R1,CURR_PTR          Point to next source record
                MVC      WTOL+4(80),0(BUFREG)
                WTO      MF=(E,WTOL)         Issue WTO for source record
                L        R1,AXPRELREC         Update
                LA       R1,1(R1)             Relative Record
                ST       R1,AXPRELREC         Number
                L        R1,AXPABSREC         Update
                LA       R1,1(R1)             Absolute Record
                ST       R1,AXPABSREC         Number
                B        EXIT1
SOURCE_EOF       DS      0H
                MVC      AXPETC,=A(AXPCEOD)  End of file on input
                B        EXIT1
                SPACE 1
*****
* SOURCE EXIT - Process WRITE request                                   *
* - Not valid for SOURCE exit.                                         *
* - Set return code to 20 and set up error message.                     *
*****
SOURCE_WRITE     DS      0H
                B        LOGICERR
                SPACE 1
*****
* SOURCE EXIT - Process PROCESS request                                 *
* - Exit may modify the record, have the assembler discard the        *
*   record or insert additional records by setting the return code      *
*   and/or reason code.                                                *
*****
SOURCE_PROCESS   DS      0H
                MVC      WTOL+4(80),0(BUFREG)
                WTO      MF=(E,WTOL)         Issue WTO for source record
                B        EXIT1
                EJECT
```

Figure 26. Example of a user exit (Part 5 of 17)



```

*****
* LIBRARY EXIT *
* - Process required request type *
*****
LIBRARY DS 0H
      L R15,AXPRTYP      Get the request type value (1-8)
      BCTR R15,0          Decrement by 1
      SLL R15,1          Multiply by 2
      LH R15,LIBRARY_ADDR(R15) Index into Address list
      AR R15,R12          Calculate the address
      BR R15             Branch to applicable routine
LIBRARY_ADDR DC Y(LIBRARY_OPEN-MYEXIT)
              DC Y(LIBRARY_CLOSE-MYEXIT)
              DC Y(LIBRARY_READ-MYEXIT)
              DC Y(LIBRARY_WRITE-MYEXIT)
              DC Y(LIBRARY_PR_MAC-MYEXIT)
              DC Y(LIBRARY_PR_CPY-MYEXIT)
              DC Y(LIBRARY_FIND_MAC-MYEXIT)
              DC Y(LIBRARY_FIND_CPY-MYEXIT)
              DC Y(LIBRARY_EOM-MYEXIT)
              DC Y(*-*)
              SPACE 1
*****
* LIBRARY EXIT - Process OPEN request *
* - Pick up character string if it is supplied. *
* - Set return code indicating whether the assembler, user exit or *
* both will process the library. *
* - Open data set if required. *
*****
LIBRARY_OPEN DS 0H
      MVI OPENPARM,C' '      Clear open parm
      MVC OPENPARM+1(L'OPENPARM-1),OPENPARM
      L R1,AXPBUFL          Get the Buffer length
      LTR R1,R1             Is string length zero?
      BZ LIBRARY_NOSTR      Yes, no string passed
      BCTR R1,0             Decrement for execute
      EX R1,UPPERSTR        Move and uppercase string
LIBRARY_NOSTR DS 0H
      CLC OPENPARM(4),=CL8'EXIT' Will user exit process library
      BE LIBRARY_OPEN_EXIT Yes
      CLC OPENPARM(4),=CL8'BOTH' Will Both process library
      BE LIBRARY_OPEN_BOTH Yes
      MVC AXPRETC,=A(0)      assembler to process library
      B EXIT1              Return
LIBRARY_OPEN_EXIT DS 0H
      OI OPENFLAG,EXIT      Set flag
      MVC AXPRETC,=A(AXPCOPN) User exit to process library
      MVC AXPREAC,=A(AXPEEOM) EXIT to get End of member calls
      B EXIT1              Return
LIBRARY_OPEN_BOTH DS 0H
      OI OPENFLAG,BOTH      Set flag
      MVC AXPRETC,=A(AXPCOPL) Both to process library
      MVC AXPREAC,=A(AXPEEOM) EXIT to get End of member calls
      B EXIT1              Return
      SPACE 1

```

Figure 26. Example of a user exit (Part 6 of 17)

## User exit coding example

```
*****
* LIBRARY EXIT - Process CLOSE request
* - Close data set if required.
* - Free storage and return.
*****
LIBRARY_CLOSE DS 0H
    USING LIBSTACK,R2          Map stack entries
    ICM R2,B'1111',STACKPTR    Check that stack is empty
    BZ FREESTOR                It should be!
LIBRARY_FREE_LOOP DS 0H
    LTR R1,R2                  Load address for FREEMAIN
    BZ FREESTOR                Finished here
    L R2,NEXT_MEM              Prepare for next loop
    LA R0,LIBSTACK_LEN         Load length for FREEMAIN
    FREEMAIN R,A=(1),LV=(0)     Free the storage acquired
    B LIBRARY_FREE_LOOP
    SPACE 1
*****
* LIBRARY EXIT - Process READ request
* - Read copy/macro source and place in buffer.
* - Set return code to 16 at end of member.
*****
LIBRARY_READ DS 0H
    ICM R2,B'1111',STACKPTR    Is the stack empty?
    BZ LIBRARY_STACK_ERR       It shouldn't be!
    L R1,MEM_PTR               Get record address
    CLI 0(R1),X'FF'            Is it EOF?
    BE LIBRARY_EOF             Yes, set return code
    MVC 0(80,BUFREG),0(R1)
    LA R1,80(,R1)               Point to next record address
    ST R1,MEM_PTR              and save in stack entry
    MVC WTOL+4(80),0(BUFREG)
    WTO MF=(E,WTOL)            Issue WTO for library record
    L R1,AXPRELREC              Update
    LA R1,1(R1)                 Relative Record
    ST R1,AXPRELREC             Number
    ST R1,MEM_RELREC            and save in stack entry
    L R1,AXPABSREC              Update
    LA R1,1(R1)                 Absolute Record
    ST R1,AXPABSREC             Number
    B EXIT1
LIBRARY_EOF DS 0H
    MVC AXPRETC,=A(AXPCEOD)     End of file on input
    B EXIT1
    SPACE 1
*****
* LIBRARY EXIT - Process WRITE request
* - Not valid for LIBRARY exit.
* - Set return code to 20 and set up error message.
*****
LIBRARY_WRITE DS 0H
    B LOGICERR
    SPACE 1
*****
* LIBRARY EXIT - Process PROCESS MACRO/COPY request
* - Exit may modify the record, have the assembler discard the
* record or insert additional records by setting the return code
* and/or reason code.
*****
LIBRARY_PR_MAC DS 0H
LIBRARY_PR_CPY DS 0H
    MVC WTOL+4(80),0(BUFREG)
    WTO MF=(E,WTOL)            Issue WTO for library record
    B EXIT1
    SPACE 1
```

Figure 26. Example of a user exit (Part 7 of 17)

```

*****
* LIBRARY EXIT - Process FIND MACRO/COPY request *
* - Search for the member. Set the return code to indicate *
* whether the member was found. *
* - If the member is found, the source information is returned. *
*****
LIBRARY_FIND_MAC DS 0H
LIBRARY_FIND_CPY DS 0H
    CLC AXPOPTS,=A(AXPORES)      Is it a resume request?
    BE LIBRARY_RESUME           Yes, resume member
    LA R3,MACA1
    CLC AXPMEMN(8),=CL8'OUTER'
    BE LIBRARY_FOUND
    LA R3,MACB1
    CLC AXPMEMN(8),=CL8'INNER'
    BE LIBRARY_FOUND
    LA R3,CPYA1
    CLC AXPMEMN(8),=CL8'TINY'
    BE LIBRARY_FOUND
    LA R3,CPYB1
    CLC AXPMEMN(8),=CL8'TINY1'
    BE LIBRARY_FOUND
    MVC AXPRETC,=A(AXPCMNF)      Indicate member not found
    B EXIT1
LIBRARY_FOUND DS 0H
    ICM R2,B'1111',STACKPTR      Is the stack empty?
    BZ LIBRARY_GET_STACK
    CLC AXPOPTS,=A(AXPONENT)      Is it a nested COPY/MACRO?
    BNE LIBRARY_STACK_ERR        NO - report an error
LIBRARY_GET_STACK DS 0H
    LA R0,LIBSTACK_LEN           Load reg with length
    GETMAIN R,LV=(0)             and getmain storage
    XC 0(LIBSTACK_LEN,R1),0(R1)  Clear the storage
NEW_LIBSTACK USING LIBSTACK,R1   Map the new stack entry
    ST R2,NEW_LIBSTACK.NEXT_MEM  Add new link to top of stack
    DROP NEW_LIBSTACK
    ST R1,STACKPTR               Re-anchor the stack
    LR R2,R1                     Make the new entry current
    ST R3,MEM_PTR                Save current record pointer
    MVC MEM_NAME,AXPMEMN         Save name in stack entry
    MVC AXPREAC,=A(AXPEISA)      Indicate source info available
    MVC AXPMEMT,=CL255'None'
    MVC AXPSN,=CL255'LIBRARY.data set.NAME'
    MVC AXPVOL,=CL255'VOL002'
    XC AXPRELREC,AXPRELREC       Set relative record No to zero
    B EXIT1
*****
* LIBRARY EXIT - Process FIND (resume) request *
* - Set the relative record number in the parameter list *
* N.B. if the EXIT read the records from disk, at this point it would *
* use the information saved in the stack to reposition itself *
* ready for the next read. (i.e. a FIND and POINT) *
*****
LIBRARY_RESUME DS 0H
    MVC AXPRETC,=A(AXPCMNF)      Assume member not found
    ICM R2,B'1111',STACKPTR      Is the stack empty?
    BZ LIBRARY_CHECK_BOTH        Yes - check open option
    CLC MEM_NAME,AXPMEMN         Compare name with stack entry
    BNE LIBRARY_CHECK_BOTH       Not equal - check open option
    MVC AXPRETC,=A(0)            Correct our assumption
    L R0,MEM_RELREC              Get saved rel rec no from stack
    ST R0,AXPRELREC              Set relative record No
    B EXIT1
SPACE 1

```

Figure 26. Example of a user exit (Part 8 of 17)

## User exit coding example

```
*****
* LIBRARY EXIT - Use End of Member calls to perform stack management *
* - Compare member name, if equal unstack the top entry *
*****
LIBRARY_EOM      DS      0H
    ICM  R2,B'1111',STACKPTR      Is the stack empty?
    BZ   LIBRARY_CHECK_BOTH      Yes - check open option
    CLC  MEM_NAME,AXPMEMN        Compare name with stack entry
    BNE  LIBRARY_CHECK_BOTH      Not equal - check open option
    LR   R1,R2                   Load address for FREEMAIN
    L    R2,NEXT_MEM             Get address of next entry
    ST   R2,STACKPTR            and save it.
    DROP R2
    LA   R0,LIBSTACK_LEN         Load length for FREEMAIN
    FREEMAIN R,A=(1),LV=(0)      Free the storage acquired
LIBRARY_CHECK_BOTH DS 0H
    CLI  OPENFLAG,BOTH          Did EXIT open with BOTH option
    BE   EXIT1                  Yes - don't issue error msg
*****
* LIBRARY EXIT - Stack Error Routine *
* - If an error occurred, set up the error message in the buffer *
*   and length in AXPERRL. Set the severity code. *
* - Set the return code to 20. *
* - Return to the caller. *
*****
LIBRARY_STACK_ERR DS 0H
    MVC  AXPRETCL=A(AXPCBAD)      Severe error occurred
    MVC  ERRBUFF(ERRMSGSL),STKMSG Set up error message
    MVC  AXPERRL=A(STKMSGSL)      Set up error message length
    MVC  AXPSEVC=A(20)           Set up error message severity
    B    EXIT1
    EJECT
*****
* LISTING EXIT *
* - Process required request type *
*****
LISTING DS 0H
    L    R15,AXPRTYP             Get the request type value (1-5)
    BCTR R15,0                   Decrement by 1
    SLL  R15,1                   Multiply by 2
    LH   R15,LISTING_ADDR(R15)   Index into Address list
    AR   R15,R12                 Calculate the address
    BR   R15                     Branch to applicable routine
LISTING_ADDR DC Y(LISTING_OPEN-MYEXIT)
             DC Y(LISTING_CLOSE-MYEXIT)
             DC Y(LISTING_READ-MYEXIT)
             DC Y(LISTING_WRITE-MYEXIT)
             DC Y(LISTING_PROCESS-MYEXIT)
             DC Y(*-*)
             SPACE 1
```

Figure 26. Example of a user exit (Part 9 of 17)

```

*****
* LISTING EXIT - Process OPEN request                                     *
* - Pick up character string if it is supplied.                         *
* - Set return code indicating whether the assembler or the user exit *
*   will write the listing.                                           *
* - Open data set if required.                                         *
*****
LISTING_OPEN    DS    0H
               MVI    OPENPARM,C' '          Clear open parm
               MVC    OPENPARM+1(L'OPENPARM-1),OPENPARM
               L      R1,AXPBUFL             Get the Buffer length
               LTR    R1,R1                  Is string length zero?
               BZ     LISTING_NOSTR          Yes, no string passed
               BCTR   R1,0                   Decrement for execute
               EX     R1,UPPERSTR            Move and uppercase string
LISTING_NOSTR    DS    0H
               CLC    OPENPARM(4),=CL8'EXIT' Will user exit process listing
               BE     LISTING_OPEN_EXIT     Yes
               MVC    AXPRETCL=A(0)         assembler to write listing
               B      EXIT1                 Return
LISTING_OPEN_EXIT DS    0H
               OI     OPENFLAG,EXIT         Set flag
               MVC    AXPRETCL=A(AXPCOPN)   User exit to write listing
               MVC    AXPMEMN,=CL255' '
               MVC    AXPMEMT,=CL255' '
               MVC    AXPDSN,=CL255'LISTING.data set.NAME'
               MVC    AXPVOL,=CL255'VOL001'
               MVC    AXPREAC,=A(AXPEISA)   Indicate data set info available
               XC     AXPRELREC,AXPRELREC    Set Relative Record No. to 0
               XC     AXPABSREC,AXPABSREC    Set Absolute Record No. to 0
               B      EXIT1                 Return
               SPACE 1
*****
* LISTING EXIT - Process CLOSE request                                   *
* - Close data set if required                                         *
* - Free storage and return.                                           *
*****
LISTING_CLOSE    DS    0H
               B      FREESTOR
               SPACE 1
*****
* LISTING EXIT - Process READ request                                   *
* - Not valid for LISTING exit.                                         *
* - Set return code to 20 and set up error message.                   *
*****
LISTING_READ     DS    0H
               B      LOGICERR
*****
* LISTING EXIT - Process WRITE request                                   *
* - Write the listing record passed.                                     *
*****
LISTING_WRITE     DS    0H
               MVC    WTOL+4(80),0(BUFREG)
               WTO    MF=(E,WTOL)           Issue WTO for listing record
               L      R1,AXPRELREC           Update
               LA     R1,1(R1)               Relative Record
               ST     R1,AXPRELREC           Number
               L      R1,AXPABSREC           Update
               LA     R1,1(R1)               Absolute Record
               ST     R1,AXPABSREC           Number
               B      EXIT1
               SPACE 1

```

Figure 26. Example of a user exit (Part 10 of 17)

## User exit coding example

```
*****
* LISTING EXIT - Process PROCESS request                                     *
* - Exit may modify the record, have the assembler discard the           *
*   record or insert additional records by setting the return code        *
*   and/or reason code.                                                  *
*****
LISTING_PROCESS DS    0H
                MVC   WTOL+4(80),0(BUFREG)
                WTO   MF=(E,WTOL)      Issue WTO for listing record
                B      EXIT1
                EJECT
*****
* OBJECT EXIT                                                             *
* - Process required request type                                         *
*****
PUNCH   DS    0H
OBJECT  DS    0H
        L      R15,AXPRTYP            Get the request type value (1-5)
        BCTR   R15,0                  Decrement by 1
        SLL    R15,1                  Multiply by 2
        LH     R15,OBJECT_ADDR(R15)   Index into Address list
        AR     R15,R12                Calculate the address
        BR     R15                    Branch to applicable routine
OBJECT_ADDR DC Y(OBJECT_OPEN-MYEXIT)
           DC Y(OBJECT_CLOSE-MYEXIT)
           DC Y(OBJECT_READ-MYEXIT)
           DC Y(OBJECT_WRITE-MYEXIT)
           DC Y(OBJECT_PROCESS-MYEXIT)
           DC Y(*-*)
           SPACE 1
*****
* OBJECT EXIT - Process OPEN request                                       *
* - Pick up character string if it is supplied.                           *
* - Set return code indicating whether the assembler or the user exit     *
*   will write the object/punch records.                                  *
* - Open data set if required                                              *
*****
OBJECT_OPEN DS    0H
        MVI    OPENPARM,C' '          Clear open parm
        MVC    OPENPARM+1(L'OPENPARM-1),OPENPARM
        L      R1,AXPBUFL             Get the Buffer length
        LTR    R1,R1                  Is string length zero?
        BZ     OBJECT_NOSTR           Yes, no string passed
        BCTR   R1,0                  Decrement for execute
        EX     R1,UPPERSTR            Move and uppercase string
OBJECT_NOSTR DS    0H
        CLC    OPENPARM(4),=CL8'EXIT' Will user exit process object
        BE     OBJECT_OPEN_EXIT      Yes
        MVC    AXPRETCL,=A(0)        assembler to write object/punch
        B      EXIT1                 Return
OBJECT_OPEN_EXIT DS 0H
        OI     OPENFLAG,EXIT          Set flag
        MVC    AXPRETCL,=A(AXPCOPN)   User exit to write object/punch
        MVC    AXPMEMN,=CL255'Member'
        MVC    AXPMEMT,=CL255' '
        MVC    AXPDSN,=CL255'OBJECT.data set.NAME'
        MVC    AXPVOL,=CL255'VOL001'
        MVC    AXPREAC,=A(AXPEISA)    Indicate data set info available
        XC     AXPRELREC,AXPRELREC     Set Relative Record No. to 0
        XC     AXPABSREC,AXPABSREC     Set Absolute Record No. to 0
        B      EXIT1                 Return
        SPACE 1
```

Figure 26. Example of a user exit (Part 11 of 17)

```

*****
* OBJECT EXIT - Process CLOSE request                                     *
* - Close data set if required.                                         *
* - Free storage and return.                                           *
*****
OBJECT_CLOSE DS 0H
              B FREESTOR
              SPACE 1
*****
* OBJECT EXIT - Process READ request                                    *
* - Not valid for OBJECT exit.                                         *
* - Set return code to 20 and set up error message.                   *
*****
OBJECT_READ DS 0H
              B LOGICERR
*****
* OBJECT EXIT - Process WRITE request                                   *
* - Write the source record passed.                                     *
*****
OBJECT_WRITE DS 0H
              MVC WTOL+4(80),0(BUFREG)
              WTO MF=(E,WTOL) Issue WTO for object record
              L R1,AXPRELREC Update
              LA R1,1(R1) Relative Record
              ST R1,AXPRELREC Number
              L R1,AXPABSREC Update
              LA R1,1(R1) Absolute Record
              ST R1,AXPABSREC Number
              B EXIT1
              SPACE 1
*****
* OBJECT EXIT - Process PROCESS request                                 *
* - Exit may modify the record, have the assembler discard the      *
* record or insert additional records by setting the return code     *
* and/or reason code.                                                *
*****
OBJECT_PROCESS DS 0H
              MVC WTOL+4(80),0(BUFREG)
              WTO MF=(E,WTOL) Issue WTO for object record
              B EXIT1
              EJECT
*****
* ADATA EXIT                                                           *
* - Process required request type                                     *
*****
ADATA DS 0H
      L R15,AXPRTPY Get the request type value (1-5)
      BCTR R15,0 Decrement by 1
      SLL R15,1 Multiply by 2
      LH R15,ADATA_ADDR(R15) Index into Address list
      AR R15,R12 Calculate the address
      BR R15 Branch to applicable routine
ADATA_ADDR DC Y(ADATA_OPEN-MYEXIT)
           DC Y(ADATA_CLOSE-MYEXIT)
           DC Y(ADATA_READ-MYEXIT)
           DC Y(ADATA_WRITE-MYEXIT)
           DC Y(ADATA_PROCESS-MYEXIT)
           DC Y(*-*)
           SPACE 1

```

Figure 26. Example of a user exit (Part 12 of 17)

## User exit coding example

```
*****
* ADATA EXIT - Process OPEN request                                     *
* - Pick up character string if it is supplied.                         *
* - Set return code indicating whether the assembler or the user exit *
*   will write the associated data.                                     *
* - Open data set if required.                                         *
*****
ADATA_OPEN    DS    0H
             MVI    OPENPARM,C' '          Clear open parm
             MVC    OPENPARM+1(L'OPENPARM-1),OPENPARM
             L      R1,AXPBUFL             Get the Buffer length
             LTR    R1,R1                  Is string length zero?
             BZ     ADATA_NOSTR            Yes, no string passed
             BCTR   R1,0                    Decrement for execute
             EX     R1,UPPERSTR             Move and uppercase string
ADATA_NOSTR    DS    0H
             CLC    OPENPARM(4),=CL8'EXIT' Will user exit process adata
             BE     ADATA_OPEN_EXIT        Yes
             MVC    AXPRETCL,=A(0)         assembler to write adata
             B      EXIT1                  Return
ADATA_OPEN_EXIT DS    0H
             OI     OPENFLAG,EXIT          Set flag
             MVC    AXPRETCL,=A(AXPCOPN)    User exit to write adata
             MVC    AXPMEMN,=CL255' '
             MVC    AXPMEMT,=CL255' '
             MVC    AXPDSN,=CL255'ADATA.data set.NAME'
             MVC    AXPVOL,=CL255'VOL001'
             MVC    AXPREAC,=A(AXPEISA)    Indicate data set info available
             XC     AXPRELREC,AXPRELREC      Set Relative Record No. to 0
             XC     AXPABSREC,AXPABSREC      Set Absolute Record No. to 0
             B      EXIT1                  Return
             SPACE 1
*****
* ADATA EXIT - Process CLOSE request                                    *
* - Close data set if required.                                         *
* - Free storage and return.                                            *
*****
ADATA_CLOSE    DS    0H
             B      FREESTOR
             SPACE 1
*****
* ADATA EXIT - Process READ request                                     *
* - Not valid for ADATA exit.                                           *
* - Set return code to 20 and set up error message.                     *
*****
ADATA_READ     DS    0H
             B      LOGICERR
*****
* ADATA EXIT - Process WRITE request                                    *
* - Write the adata record passed.                                       *
*****
ADATA_WRITE     DS    0H
             MVC    WTOL+4(80),0(BUFREG)
             WTO    MF=(E,WTOL)             Issue WTO for adata record
             L      R1,AXPRELREC             Update
             LA     R1,1(R1)                 Relative Record
             ST     R1,AXPRELREC             Number
             L      R1,AXPABSREC             Update
             LA     R1,1(R1)                 Absolute Record
             ST     R1,AXPABSREC             Number
             B      EXIT1
             SPACE 1
```

Figure 26. Example of a user exit (Part 13 of 17)



```

*****
* ADATA EXIT - Process PROCESS request                                     *
* - Exit may modify the record, have the assembler discard the          *
*   record or insert additional records by setting the return code        *
*   and/or reason code.                                                 *
*****
ADATA_PROCESS DS      0H
              MVC     WTOL+4(80),0(BUFREG)
              WTO     MF=(E,WTOL)           Issue WTO for ADATA record
              B       EXIT1
              EJECT
*****
* TERM EXIT                                                                *
* - Process required request type                                         *
*****
TERM         DS      0H
              L       R15,AXPRTYP           Get the request type value (1-5)
              BCTR    R15,0                 Decrement by 1
              SLL     R15,1                 Multiply by 2
              LH      R15,TERM_ADDR(R15)    Index into Address list
              AR      R15,R12               Calculate the address
              BR      R15                   Branch to applicable routine
TERM_ADDR DC Y(TERM_OPEN-MYEXIT)
           DC Y(TERM_CLOSE-MYEXIT)
           DC Y(TERM_READ-MYEXIT)
           DC Y(TERM_WRITE-MYEXIT)
           DC Y(TERM_PROCESS-MYEXIT)
           DC Y(*-*)
           SPACE 1
*****
* TERM EXIT - Process OPEN request                                         *
* - Pick up character string if it is supplied.                           *
* - Set return code indicating whether the assembler or the user exit     *
*   will write the terminal records.                                       *
* - Open data set if required.                                             *
*****
TERM_OPEN    DS      0H
              MVI     OPENPARM,C' '         Clear open parm
              MVC     OPENPARM+1(L'OPENPARM-1),OPENPARM
              L       R1,AXPBUFL           Get the Buffer length
              LTR     R1,R1                 Is string length zero?
              BZ      TERM_NOSTR            Yes, no string passed
              BCTR    R1,0                 Decrement for execute
              EX      R1,UPPERSTR           Move and uppercase string
TERM_NOSTR   DS      0H
              CLC     OPENPARM(4),=CL8'EXIT' Will user exit process records?
              BE      TERM_OPEN_EXIT       Yes
              MVC     AXPRETC,=A(0)        assembler to write records
              B       EXIT1                Return
TERM_OPEN_EXIT DS    0H
              OI      OPENFLAG,EXIT        Set flag
              MVC     AXPRETC,=A(AXPCOPN)   User exit to write records
              MVC     AXPMEMN,=CL255' '
              MVC     AXPMEMT,=CL255' '
              MVC     AXPSN,=CL255'TERM.data set.NAME'
              MVC     AXPVOL,=CL255'VOL001'
              MVC     AXPREAC,=A(AXPEISA)   Indicate data set info available
              XC      AXPRELREC,AXPRELREC   Set Relative Record No. to 0
              XC      AXPABSREC,AXPABSREC   Set Absolute Record No. to 0
              B       EXIT1                Return
              SPACE 1

```

Figure 26. Example of a user exit (Part 14 of 17)

## User exit coding example

```
*****
* TERM EXIT - Process CLOSE request                                     *
* - Close data set if required.                                       *
* - Free storage and return.                                          *
*****
TERM_CLOSE      DS      0H
                B        FREESTOR
                SPACE 1
*****
* TERM EXIT - Process READ request                                    *
* - Not valid for TERM exit.                                         *
* - Set return code to 20 and set up error message.                  *
*****
TERM_READ       DS      0H
                B        LOGICERR
*****
* TERM EXIT - Process WRITE request                                   *
* - Write the terminal record passed.                                 *
*****
TERM_WRITE      DS      0H
                MVC      WTOL+4(68),0(BUFREG)
                WTO      MF=(E,WTOL)           Issue WTO for terminal record
                L        R1,AXPRELREC          Update
                LA       R1,1(R1)             Relative Record
                ST       R1,AXPRELREC          Number
                L        R1,AXPABSREC          Update
                LA       R1,1(R1)             Absolute Record
                ST       R1,AXPABSREC          Number
                B        EXIT1
                SPACE 1
*****
* TERM EXIT - Process PROCESS request                                *
* - Exit may modify the record, have the assembler discard the      *
*   record or insert additional records by setting the return code   *
*   and/or reason code.                                             *
*****
TERM_PROCESS    DS      0H
                MVC      WTOL+4(68),0(BUFREG)
                WTO      MF=(E,WTOL)           Issue WTO for terminal record
                B        EXIT1
STKMSG          DC      C'LIBRARY EXIT encountered a stack error'
STKMSG          EQU      *-ERRMSG
ERRMSG          DC      C'Invalid EXIT type or Request type passed to exit'
ERRMSG          EQU      *-ERRMSG
WTOL            WTO      '1234567890123456789012345678901234567890123456789012345X
6789012345678901234567890',MF=L
UPPERSTR        OC      OPENPARM(*-*),0(BUFREG) Move and uppercase string
                SPACE 1
```

Figure 26. Example of a user exit (Part 15 of 17)

---

```

SRC1    DC    CL80'SMALL    TITLE  'Test the assembler exits'''
SRC2    DC    CL80'        MACRO'
SRC3    DC    CL80'        LITTLE'
SRC4    DC    CL80'        BSM  0,14  Return'
SRC5    DC    CL80'        MEND'
SRC6    DC    CL80'        START'
SRC7    DC    CL80'        OUTER'
SRC8    DC    CL80'        LITTLE'
SRC9    DC    CL80'        REPRO'
SRC10   DC    CL80'This is to be written to the punch data set'
SRC11   DC    CL80'        COPY  TINY'
SRC12   DC    CL80'        END'
SRCEND  DC    X'FF'        END OF SOURCE STMTS
        SPACE 1
MACA1   DC    CL80'        MACRO'
MACA2   DC    CL80'        OUTER'
MACA3   DC    CL80'        XR    15,15'
MACA4   DC    CL80'        INNER'
MACA5   DC    CL80'        LTR  15,15'
MACA6   DC    CL80'        MEND'
MACAEND DC    X'FF'        END OF MACRO STMTS
        SPACE 1
MACB1   DC    CL80'        MACRO'
MACB2   DC    CL80'        INNER'
MACB3   DC    CL80'        LR    12,15'
MACB4   DC    CL80'        MEND'
MACBEND DC    X'FF'        END OF MACRO STMTS
        SPACE 1
CPYA1   DC    CL80'TINY    DSECT                LINE 1 TINY'
CPYA2   DC    CL80'        DS    C'TINY'        LINE 2 TINY'
CPYA3   DC    CL80'        COPY  TINY1         LINE 3 TINY'
CPYA4   DC    CL80'        DS    CL10'TINY'     LINE 4 TINY'
CPYA5   DC    CL80'        DS    CL80          LINE 5 TINY'
CPYEND  DC    X'FF'        END OF COPY STMTS
CPYB1   DC    CL80'TINY1   DSECT                LINE 1 TINY1'
CPYB2   DC    CL80'        DS    C'TINY1'       LINE 2 TINY1'
CPYB3   DC    CL80'        DS    CL10'TINY1'    LINE 3 TINY1'
CPYBEND DC    X'FF'        END OF COPY STMTS
        SPACE 1
R0      EQU    0
R1      EQU    1
R2      EQU    2
R3      EQU    3
R4      EQU    4
R5      EQU    5
R6      EQU    6
R7      EQU    7
R8      EQU    8
R9      EQU    9
R10     EQU    10
R11     EQU    11
R12     EQU    12
R13     EQU    13
R14     EQU    14
R15     EQU    15
DCBREG  EQU    5           Address of DCB
SRCREG  EQU    6           Address of Source Information
ERRREG  EQU    7           Address of Error Buffer
BUFREG  EQU    8           Address of buffer
REQREG  EQU    9           Address of request information
PARMREG EQU    10          Address or parameter

```

---

Figure 26. Example of a user exit (Part 16 of 17)

---

	LTORG ,	
	SPACE 1	
	DCBD DSORG=PS,DEV=DA	
	SPACE 1	
	ASMAXITP ,	Mapping for exit parameter list
	SPACE 1	
BUFF	DSECT ,	
	DS CL255	Record buffer
	SPACE 1	
ERRBUFF	DSECT ,	
	DS CL255	Error message buffer
	SPACE 1	
WORKAREA	DSECT	
SAVEAREA	DS 18F	Save area
OPENPARM	DS CL64	Character string passed at open time
OPENFLAG	DS X	Type of Operation requested at OPEN
EXIT	EQU X'80'	
BOTH	EQU X'C0'	
LASTOP	DS X	Previous request type
CURR_PTR	DS A	Current record pointer
STACKPTR	DS A	Address of top of Lib status stack
WORKLEN	EQU *-WORKAREA	
LIBSTACK	DSECT	Library status stack entry
NEXT_MEM	DS A	Address of entry next in stack
MEM_PTR	DS A	Current record pointer
MEM_RELREC	DS F	Current relative record number
MEM_NAME	DS CL64	Stack of saved member names
LIBSTACK_LEN	EQU *-LIBSTACK	
END	MYEXIT	

---

*Figure 26. Example of a user exit (Part 17 of 17)*

---

## Chapter 5. Providing external functions

Two conditional assembly instructions, SETAF and SETCF, let you call routines written in a programming language that conforms to standard OS Linkage conventions. The assembler calls the external function load module and passes the address of an external function parameter list in Register 1. Each differently-named external function called in the same assembly is provided with a separate parameter list.

The SETAF instruction calls an external function module, and passes to the module any number of parameters containing *arithmetic* values. The SET symbol in the instruction is assigned the fullword value returned by the external function module.

The SETCF instruction calls an external function module, and passes to the module any number of parameters containing *character* values. The SET symbol in the instruction is assigned the character string value returned by the external function module. The character string value can be up to 1024 characters long.

This chapter describes the external function processing requirements, the linkage conventions for generating an external function module, and the contents of the parameter list that the assembler passes to the module

---

### External function processing

The assembler calls an external function each time it processes a SETAF or SETCF instruction. The assembler loads the external function module when the first call to the module is encountered. The assembler expects the external function module to be generated in 31-bit addressing mode (AMODE 31). The external function must return to the assembler in the same addressing mode from which it was called after restoring the registers to the values they contained at the time of the call. Only one copy of the load module is loaded, so it must be serially reusable. The assembler must be able to locate the external function module as follows:

---

#### z/OS

The external function must be a link-edited load module in a partitioned data set, or a program object in a PDSE, that is in the standard search sequence. The external function can also be located in the Link Pack Area (LPA).

---

End of z/OS

---

#### z/VM

The external function must have a file type of MODULE and be located on one of the accessed disks. To generate the module, use the CMS LOAD and GENMOD commands. When the LOAD command is issued, specify the RLDSAVE option to make the module relocatable. If RLDSAVE is not specified, the assembler program or data storage might be overlaid during execution.

---

End of z/VM

## External function processing

z/VSE

The external function must be a relocatable phase in a sublibrary that is specified in the LIBDEF phase search chain. The external function can also be located in the Shared Virtual Area (SVA).

End of z/VSE

**Using the SIZE Option to Reserve Storage:** External function modules are loaded by the assembler during the assembly, which is after the assembler completes initialization. Therefore, you should allow enough virtual storage in the address space (z/OS and CMS) or the partition (z/VSE) in which the assembler runs, so that the external function modules can be loaded successfully, and for any storage that your external function might acquire. You can reserve storage for your external function modules by reducing the amount of storage the assembler uses. Use the SIZE assembler option to control the amount of storage the assembler uses.

## Linkage conventions

External function modules are called by the assembler using standard OS Linkage conventions. The external function can be written in any language that:

- Uses standard OS linkage conventions.
- Can be called many times using the module (or phase) entry point.
- Retains storage for variables across invocations and does not require a run-time environment to be maintained across invocations.

See the specific programming language *Programmer's Guide* to determine if you can use the programming language to write an external function for the High Level Assembler.

The contents of the registers upon entry to the external function are as follows:

<b>Register 0</b>	Undefined
<b>Register 1</b>	Address of external function parameter list
<b>Registers 2 through 12</b>	Undefined
<b>Register 13</b>	Address of the 72 byte register save area
<b>Register 14</b>	Return address
<b>Register 15</b>	Address of entry point of external function

## External function parameter list

The assembler passes a parameter list to the external function module. Register 1 points to the parameter list, and macro ASMAEFNP maps the parameter list. Figure 27 on page 147 shows the SETAF parameter list, and Figure 28 on page 148 shows the SETCF parameter list. A separate copy of the external function parameter list is passed to each external function. The sections following the figures describe each of the parameters in detail.




Figure 27. SETAF external function parameter list format




Figure 28. SETCF external function parameter list format

The external function parameter list consists of the following addresses:

### Request information list

Pointer to a list of binary fullword items that describe the external function request. The assembler sets this pointer, which is always valid.

The Request Information List consists of these fields:



**Parameter list version**

A fullword identifying which version of the parameter list is provided to the external function. For High Level Assembler Release 6 this field contains a value of 3.

**Function type**

A fullword, set by the assembler to indicate the function type:

- 0 CLOSE call
- 1 SETAF function
- 2 SETCF function

**Number of parameters**

A fullword indicating the number of parameters provided on the call to this external function.

The assembler always sets this field.

**Return code**

A fullword, set by the external function, indicating success or failure of the operation, and action to be taken by the assembler on return from the external function:

- 0 Operation successful. Value or string returned.
- >0 Operation failed. Request assembler to terminate immediately.

When the return code is greater than 0 the assembler issues diagnostic error message ASMA941U.

**Flag byte**

X'80' Function requests a CLOSE call.

The CLOSE call is not enabled by default. Each time the external function is called, it is able to set (or reset) this flag to indicate that it needs to perform some extra processing (releasing storage, for example) before being deleted. The external function may therefore set the flag on one call and reset it on another.

If the flag is set at the end of the assembly, HLASM will call the function with a CLOSE code to allow it to release resources.

The assembler maintains the Flag Byte and provides it to the external function on all calls.

**Reserved**

This storage is reserved for future use by IBM. The external function should not use this field, nor should it rely on the contents of this field (which are liable to change without notice).

External functions can request that a message be issued on their behalf. The function provides the text of the message, and the assembler inserts the function's name and the supplied text into one of five messages. The relevant information is contained in two fields, **Message Length** and **Message Severity**:

## External function parameter list

### Msg length

A halfword, set by the external function, indicating the length of the message to be issued.

### Msg severity

A halfword, set by the external function, from which the assembler determines the associated message number. The severity code returned by the function is rounded up to a multiple of four as shown in Table 22.

Table 22. Message severity and associated messages

Severity Code Specified	Severity Code Used	Associated Message
0	0	ASMA710I
1–4	4	ASMA711W
5–8	8	ASMA712E
9–12	12	ASMA713S
>12	16	ASMA714C

### Return value (SETAF)

A fullword, set by the external function. This field is set to zero by the assembler before the external function call.

### Parm value *n* (SETAF)

A fullword, set by the assembler, containing the value of the parameter passed to the external function.

The **Number of Parameters** field indicates the number of **Parm Value *n*** fields in the Request Information List.

### Return string length (SETCF)

An unsigned fullword, set by the external function, containing the length of the string pointed to by the **Pointer to Parm String** field.

The assembler uses this field as the length of the returned string.

If the length is greater than 1024, it is reset to 1024 by the assembler. The consequence of returning a string longer than 1024 bytes is unpredictable.

### Parm string *n* length (SETCF)

An unsigned fullword, set by the assembler, containing the length of the string pointed to by the **Ptr to Parm String *n*** field.

The external function should use this length to determine the length of the Parm String *n* passed by the assembler.

The assembler sets this field to a value between 0 and 1024 inclusive.

The **Number of Parameters** field indicates the number of **Parm String *n* Length** fields in the Request Information List.

## Pointer to user work area

Pointer to the User Work Area.

The assembler provides four double words of storage for use by the external function. This storage is double-word aligned and the assembler initializes it to zero for the first call to the external function.

It can be used by the external function to store information (such as the address of acquired storage) between calls. The contents of this storage area are preserved across all call types (SETAF, SETCF, and CLOSE) until the assembly completes. The assembler does not use or modify the work area.

### Pointer to static assembler information

Pointer to the Static Assembler Information.

This is pointed to by the Static Assembler Information Pointer. See “Static assembler information pointer” on page 99.

### Pointer to msg buffer

Pointer to the “function-supplied message” area.

The assembler always sets this pointer before invoking an external function. The external function can put up to 255 bytes of message text into the area addressed by this field.

### Pointer to return string (SETCF)

Pointer to the string returned by the external function.

The assembler always sets this pointer before invoking an external function. The external function can put up to 1024 bytes of character string data into the area addressed by this field.

### Pointer to parm string *n* (SETCF)

Pointer to **Parm String *n*** passed to the external function.

The assembler always sets this pointer before invoking an external function. The length of the string pointed to by this field is contained in the **Parm String *n* Length** field.

The **Number of Parameters** field in the Request Information List indicates the number of **Pointer to Parm String *n*** fields in the External Function Parameter List.



---

## Chapter 6. Diagnosing assembly errors

The diagnostic facilities for High Level Assembler include:

- Diagnostic messages for assembly errors.
- A macro trace and dump facility (MHELP).
- Messages and dumps issued by the assembler if it ends abnormally.
- Diagnostic or explanatory messages issued by the source program or by macro definitions (MNOTEs).

This chapter provides an overview of these facilities. The assembly error diagnostic messages and abnormal assembly termination messages are described in detail in Appendix G, “High Level Assembler messages,” on page 335.

---

### Assembly error diagnostic messages

High Level Assembler prints most error messages in the listing immediately following the statement in error. It also prints the total number of flagged statements and their statement numbers in the Diagnostic Cross Reference and Assembler Summary section of the assembler listing.

The messages do not follow the statement in error when:

- Errors are detected during editing of macro definitions read from a library. A message for such an error appears after the first call in the source program to that macro definition. You can, however, bring the macro definition into the source program with a COPY statement or using the LIBMAC assembler option. The editing error messages then follow immediately after the statements in error.
- Errors are detected by the lookahead function of the assembler. (For attribute references, look-ahead processing scans for symbols defined on statements after the one being assembled.) Messages for these errors appear after the statements in which they occur. The messages may also appear at the point at which lookahead was called.
- Errors are detected on conditional assembler statements during macro generation or MHELP testing. Such a message follows the most recently generated statement or MHELP output statement.

A typical error diagnostic message is:

```
** ASMA057E UNDEFINED OPERATION CODE - xxxxxxxx
```

A copy of a segment of the statement in error, represented above by xxxxxxxx, is appended to the end of many messages. Normally this segment begins at the bad character or term. For some errors, however, the segment begins after the bad character or term.

If a diagnostic message follows a statement generated by a macro definition, the following items might be appended to the error message:

- The number of the model statement in which the error occurred, or the first five characters of the macro name.
- The SET symbol, system variable, macro parameter, or value string associated with the error.

## Assembly error diagnostic messages

**Macro Parameters:** Messages may reference three types of macro parameter: the *name field* parameter, *keyword* parameters, and *positional* parameters. A reference to the name field parameter is indicated by the word “NAME” appended to the message. References to keyword and positional parameters (for which there may be multiple occurrences) are in the form “KPARAM $nnnn$ ” and “PPARM $nnnn$ ” respectively, where  $nnnn$  is the relative number of the parameter within the macro definition.

Figure 29 shows an example of a macro with messages referencing each type of variable or parameter.

Active Usings: None				HLASM R6.0 2008/07/11 17.48	
Loc	Object Code	Addr1	Addr2	Stmt	Source Statement
				1	MACRO
				2	parms &kw1=a,&kw2=b,&kw3=c,&kw4=d,&kw5=e,&kw6=f,&pp1,&pp2
				3	&c SETC 'just a string'
				4	&ss SETA &c
				5	&sv SETA &sysasm
				6	&z1 SETA &z
				7	&k1 SETA &kw1
				8	&k5 SETA &kw5
				9	&n SETA n'&syslist
				10	&pn SETA &syslist(&n)
				11	&p2 SETA &pp2
				12	MEND
000000		00000	00000	13	default CSECT
				14	n parms pp1,pp2,kw5=z,pp3,kw1=y,pp4,pp5,pp6
ASMA102E	Arithmetic term is not self-defining term; default=0 - 00004/C				
ASMA102E	Arithmetic term is not self-defining term; default=0 - 00005/SYSASM				
ASMA102E	Arithmetic term is not self-defining term; default=0 - 00006/Z				
ASMA102E	Arithmetic term is not self-defining term; default=0 - 00007/KPARAM00001				
ASMA102E	Arithmetic term is not self-defining term; default=0 - 00008/KPARAM00005				
ASMA102E	Arithmetic term is not self-defining term; default=0 - 00010/PPARM00006				
ASMA102E	Arithmetic term is not self-defining term; default=0 - 00011/PPARM00002				
				15	END
					00015000

Figure 29. Sample macro parameter messages

### Notes to Figure 29:

- 1 SET symbol, and related message
- 2 System variable symbol, and related message
- 3 The name field parameter, and related message
- 4 Keyword parameters, and related messages
- 5 Positional parameters, and related messages

**Conditional Assembly:** If a diagnostic message follows a conditional assembly statement in the source program, the following items are appended to the error message:

- The word “OPENC”, meaning “open code”.
- The SET symbol, or value string, associated with the error.

**Multiple Messages:** Several messages can be issued for a single statement or even for a single error within a statement. This happens because each statement is usually evaluated on more than one level (for example, term level, expression level, and operand level) or by more than one phase of the assembler. Each level or phase can diagnose errors; therefore, most or all of the errors in the statement are flagged. Occasionally, duplicate error messages may occur. This is a normal result of the error detection process.

Figure 30 is an example of High Level Assembler handling of error messages, and includes message ASMA435I to show the effect of the FLAG(RECORD) assembler option.

## MNOTE statements

An MNOTE statement is included in a macro definition or in the source program. It causes the assembler to generate an inline error or informational message.

An MNOTE appears in the listing as follows:

ASMA254I \*\*\*MNOTE\*\*\* *statement number, severity code, message*

Unless the severity code is shown as an asterisk (\*), or the severity code is omitted, the statement number of the MNOTE is listed in the diagnostic cross-reference.

---

Active Usings: None					HLASM R6.0 2008/07/11 17.48	
Loc	Object Code	Addr1	Addr2	Stmnt	Source Statement	
				1	*****	DIA00010
				2	* SAMPLE ERROR DIAGNOSTIC MESSAGES	* DIA00020
				3	* IN SOURCE PROGRAM (OPEN CODE) AND GENERATED BY MACRO CALLS	* DIA00030
				4	*****	DIA00040
000000		00000	0003C	5	A CSECT	DIA00050
000000	0000	0000	00000	6	STM 14,U2,12(13{	DIA00060
** ASMA044E Undefined symbol - U2						
** ASMA029E Incorrect register specification - U2						
** ASMA179S Delimiter error, expected right parenthesis - (						
** ASMA435I Record 6 in DIAGMSG ASSEMBLE A1 on volume: ADISK						
000004	05C0			7	BALR 12,0	DIA00070
		R:C	00006	8	USING *,12	DIA00080
000006	0000	0000	00000	9	ST 13,SAVE+4	DIA00090
** ASMA044E Undefined symbol - SAVE						
** ASMA435I Record 9 in DIAGMSG ASSEMBLE A1 on volume: ADISK						
				10	OPEN (CRDIN,(INPUT),CRDOUT,(OUTPUT)	DIA00100
** ASMA088E Unbalanced parentheses in macro call operand - OPEN /(CRDIN,(INPUT),CRDOUT,(OUTPUT)						
** ASMA435I Record 323 in OSMACRO MACLIB S2(OPEN) on volume: MNT190						
00000A	0700			11+	CNOP 0,4	ALIGN LIST TO FULLWORD 01-OPEN
00000C	4110	C00E	00014	12+	LA 1,++8	LOAD R1 W/LIST ADR @V6PXJRU 01-OPEN
000010	47F0	C00E	00014	13+	B ++4	BRANCH AROUND LIST @V6PXJRU 01-OPEN
** ASMA254I *** MNOTE ***						
				14+	12,*** IHB001 DCB OPERAND REQ'D-NOT SPECIFIED	02-IHBER
				15	DROP 11	DIA00110
** ASMA045W Register or label not previously used - 11						
** ASMA435I Record 11 in DIAGMSG ASSEMBLE A1 on volume: ADISK						

---

Figure 30. Sample error diagnostic messages (Part 1 of 4)

---

				16	*****	DIA00120
				17	* EDITING AND GENERATION ERRORS AND MNOTES FROM A LIBRARY MACRO	* DIA00130
				18	*****	DIA00140
				19	LOADR REG1=10,REG2=8,WOOSHA,SUMA	DIA00150
000014	58A0	C02E	00034	20+	L 10,WOOSHA	01-LOADR
000018	5880	C032	00038	21+	L 8,SUMA	01-LOADR
				22	LOADR REG1=25,REG2=8,WOOSHA,MAINY	DIA00160
00001C	0000	0000	00000	23+	L 25,WOOSHA	01-LOADR
** ASMA029E Incorrect register specification - 25						
** ASMA435I Record 5 in TEST MACLIB A1(LOADR) on volume: ADISK						
000020	0000	0000	00000	24+	L 8,MAINY	01-LOADR
** ASMA044E Undefined symbol - MAINY						
** ASMA435I Record 6 in TEST MACLIB A1(LOADR) on volume: ADISK						
				25	LOADR REG2=10,SUMA,MAINY	DIA00170
** ASMA254I *** MNOTE ***						
				26+	36,YOU LEFT OUT THE FIRST REGISTER	01-LOADR

---

Figure 30. Sample error diagnostic messages (Part 2 of 4)

## MNOTE statements

```
27 ***** DIA00180
28 *      SAMPLE IN-LINE MACRO DEFINITION * DIA00190
29 ***** DIA00200
30      MACRO DIA00210
31 &NAME  LOADR &REG1=,&REG2=,&OP1,&OP2 DIA00220
32 &R(1)  SETA  &REG1,&REG2 DIA00230
33      AIF  (T'&REG1 EQ '0').ERR DIA00240
34      L    &R(1),&OP1 DIA00250
35      L    &R(2),&OP2 DIA00260
36      MEXIT DIA00270
37 .ERR   MNOTE 36,'YOU LEFT OUT THE FIRST REGISTER' DIA00280
38      MEND DIA00290
```

Figure 30. Sample error diagnostic messages (Part 3 of 4)

```
39 ***** DIA00300
40 *      SAMPLE MACRO CALLS WITH GENERATION ERRORS AND MNOTES * DIA00310
41 ***** DIA00320
                                     Page 4

Active Usings: A+X'6',R12
Loc  Object Code  Addr1 Addr2  Stmt  Source Statement                                     HLASM R6.0  2008/07/11 17.48
000024 58A0 C02E      00034 43+   L    10,WOOSHA DIA00330
000028 58B0 C032      00038 44+   L    8,SUMA DIA00340
                                     45   LOADR REG1=25,REG2=8,WOOSHA,&MAINY DIA00340
** ASMA003E Undeclared variable symbol; default=0, null, or type=U - OPENC/MAINY
** ASMA435I Record 34 in DIAGMSG ASSEMBLE A1 on volume: ADISK
00002C 0000 0000      00000 46+   L    25,WOOSHA 01-00034
** ASMA029E Incorrect register specification - 25
** ASMA435I Record 25 in DIAGMSG ASSEMBLE A1 on volume: ADISK
000030 0000 0000      00000 47+   L    8, DIA00350
** ASMA074E Illegal syntax in expression -
** ASMA435I Record 26 in DIAGMSG ASSEMBLE A1 on volume: ADISK
                                     48   LOADR REG2=8,SUMA,MAINY DIA00350
** ASMA254I *** MNOTE ***
000034      49+   36,YOU LEFT OUT THE FIRST REGISTER 01-00037
000038      50 WOOSHA DS F DIA00360
                                     51 SUMA DS F DIA00370
                                     52 END DIA00380
```

Figure 30. Sample error diagnostic messages (Part 4 of 4)

## Suppression of error messages and MNOTE statements

Optionally, you can suppress error messages and MNOTE statements below a specified severity level by specifying the assembler option FLAG(*n*) (where *n* is the lowest severity message that the assembler issues).

## Reference information for statements in error

The FLAG(RECORD) assembler option instructs the assembler to issue message ASMA435I after the last error message for each statement in error. This message shows reference information, including the data set name, and member name (if applicable), and the input record number of the statement in error. When you specify this option, the assembler includes reference information with the flagged statements in the Diagnostic Cross Reference and Assembler Summary section of the assembler listing. The reference information includes:

- The member name (if applicable).
- The input record number of the statement in error.
- The input data set concatenation value.

## Abnormal assembly termination

Whenever the assembly cannot complete, High Level Assembler provides a message and, in some cases, a specially formatted dump for diagnostic information. This might indicate an assembler malfunction or it might indicate a programmer error. The statement causing the error is identified and, if possible, the



assembly listing up to the point of the error is printed. Appendix G, “High Level Assembler messages,” on page 335 describes the abnormal termination messages. The messages give enough information to enable you (1) to correct the error and reassemble your program, or (2) to determine that the error is an assembler malfunction.

---

## MHELP—macro trace facility

The MHELP instruction controls a set of trace and dump facilities. You select options by specifying an absolute expression in the MHELP operand field. MHELP statements can occur anywhere in open code or in macro definitions. MHELP options remain in effect until superseded by another MHELP statement.

**Format of MHELP:**

---

Name	Operation	Operand
	MHELP	Absolute expression, (the sum of binary or decimal options)

---

- The options are:
- B'1' or 1** Macro Call Trace
  - B'10' or 2** Macro Branch Trace
  - B'100' or 4** Macro AIF Dump
  - B'1000' or 8** Macro Exit Dump
  - B'10000' or 16** Macro Entry Dump
  - B'100000' or 32** Global Suppression
  - B'1000000' or 64** Macro Hex Dump
  - B'10000000' or 128** Suppression
  - Other values** Control on &SYSNDX

Refer to Appendix F, “MHELP sample macro trace and dump,” on page 325 for complete details about this facility.



---

## Part 2. Developing assembler programs on z/OS

<b>Chapter 7. Assembling your program on z/OS</b>	161	EXEC statements . . . . .	191
Input to the assembler . . . . .	161	DD statements . . . . .	191
Output from the assembler . . . . .	161	Examples of cataloged procedures . . . . .	191
Invoking the assembler on z/OS . . . . .	161	Operating system programming conventions . . . . .	192
Invoking the assembler on TSO . . . . .	163	Saving and restoring general register contents . . . . .	193
Invoking the assembler dynamically . . . . .	164	Ending program execution . . . . .	193
Batch assembling . . . . .	166	Accessing execution parameters . . . . .	194
Input and output data sets . . . . .	166	Object program linkage . . . . .	194
Specifying the source data set: SYSIN . . . . .	169	Modifying program modules . . . . .	195
Specifying the option file: ASMAOPT . . . . .	170		
Specifying macro and copy code libraries:			
SYSLIB . . . . .	170		
Specifying the listing data set: SYSPRINT . . . . .	170		
Directing assembler messages to your terminal:			
SYSTEM . . . . .	170		
Specifying object code data sets: SYSLIN and			
SYSPUNCH . . . . .	171		
Specifying the associated data data set:			
SYSADATA . . . . .	171		
Return codes . . . . .	171		
 <b>Chapter 8. Linking and running your program</b>			
<b>on z/OS</b> . . . . .	173		
The program management binder . . . . .	173		
The loader . . . . .	174		
Creating a load module . . . . .	175		
Creating a load module on z/OS . . . . .	175		
Creating a load module on TSO . . . . .	175		
Examples using the LINK command . . . . .	175		
Input to the binder . . . . .	176		
Data sets for binder processing . . . . .	177		
Additional object modules as input . . . . .	177		
Output from the binder . . . . .	178		
Binder processing options . . . . .	178		
Specifying binder options through JCL . . . . .	179		
Specifying binder options using the TSO LINK			
command . . . . .	180		
AMODE and RMODE attributes . . . . .	180		
Overriding the defaults . . . . .	181		
Detecting binder errors . . . . .	181		
Running your assembled program . . . . .	181		
Running your assembled program in batch . . . . .	181		
Running your assembled program on TSO . . . . .	182		
 <b>Chapter 9. z/OS system services and</b>			
<b>programming considerations</b> . . . . .	183		
Adding definitions to a macro library . . . . .	183		
Using cataloged procedures . . . . .	184		
Cataloged procedure for assembly (ASMAC) . . . . .	184		
Cataloged procedure for assembly and link			
(ASMACL) . . . . .	185		
Cataloged procedure for assembly, link, and run			
(ASMACLG) . . . . .	187		
Cataloged procedure for assembly and run			
(ASMACG) . . . . .	189		
Overriding statements in cataloged procedures . . . . .	190		



---

## Chapter 7. Assembling your program on z/OS

This chapter describes how to invoke the assembler on z/OS. It describes:

- The input to the assembler.
- The output from the assembler.
- How to invoke the assembler on z/OS and TSO.
- How to invoke the assembler dynamically from a program.
- How to assemble multiple source programs using the BATCH option.
- The data sets used by the assembler.
- The assembler return codes.
- The cataloged procedures of job control language supplied by IBM.

---

### Input to the assembler

As input, the assembler accepts a program written in the assembler language as defined in the *HLASM Language Reference*. This program is referred to as a source module. Some statements in the source module (macro or COPY instructions) may cause additional input to be obtained from a macro library.

Input can also be obtained from user exits. See Chapter 4, “Providing user exits,” on page 87 for more information.

---

### Output from the assembler

The output from the assembler can consist of an object module, a program listing, terminal messages, and an associated data file. The object module can be written to a data set residing on a direct access device or a magnetic tape. If you specify the GOFF assembler option, the assembler produces a generalized object format module. Both formats of the object module are written to the same data set, however only one format can be produced at a time. From that data set, the object module can be read and processed by the linkage editor, the batch loader, or the z/OS binder. See Appendix C, “Object deck output,” on page 259 for the format of the object module. The format of the generalized object format module is described in *z/OS MVS Program Management: Advanced Facilities*.

The program listing shows all the statements in the module, both in source and machine language format, and gives other important information about the assembly, such as error messages and cross reference information. The listing is described in detail in Chapter 2, “Using the assembler listing,” on page 7.

---

### Invoking the assembler on z/OS

The JCL for running an assembly includes:

- A job description.
- A statement to run the assembler.
- Definitions for the data sets needed.

The simplest way to assemble your program on z/OS is to code JCL that uses the cataloged procedure shown in Figure 31 on page 162.

---

```
//jobname JOB accountno,progrname,MSGLEVEL=1
//stepname EXEC ASMAC
//SYSIN DD *
:
Assembler source statements
:
/*
```

---

Figure 31. JCL for assembly, using cataloged procedure

- 1** Identifies the beginning of your job to the operating system. *jobname* is the name you assign to the job. *accountno* specifies the account to which your job is charged, and *progrname* is the name of the programmer responsible for the job. MSGLEVEL=1 specifies that the job control statements connected with this job are to be listed. Check what parameters are required at your installation and how they must be specified.
- 2** Calls the cataloged procedure ASMAC. As a result, a number of job control statements are included in the job from the procedure library. ASMAC is described under “Cataloged procedure for assembly (ASMACH)” on page 184; an expanded job stream is shown there.
- 3** Specifies that the assembler language source program follows immediately after this statement.

These statements cause the assembler to assemble your program, produce a listing and write an object module to the SYSLIN data set. If you do not want an object module written to the SYSLIN data set, use the following job control statements to assemble the program:

---

```
//jobname JOB accountno,progrname,MSGLEVEL=1
//stepname EXEC ASMAC,PARM=NOOBJECT
//SYSIN DD *
:
Assembler source statements
:
/*
```

---

Figure 32. JCL for assembly, using cataloged procedure, with NOOBJECT

**Assembler Options:** The second parameter (PARM) specifies the assembler option NOOBJECT, which tells the assembler not to write the object module to SYSLIN. For a full discussion of assembler options, see Chapter 3, “Controlling your assembly with options,” on page 39.

**Using your own JCL:** The cataloged procedures might not comply with your data processing requirements. Figure 33 on page 163 shows sample job control statements that you can use instead to assemble your program.

```
//ASMJOB   JOB   1,MSGLEVEL=1
//ASSEMBLY EXEC PGM=ASMA90,PARM=OBJECT
//SYSPRINT DD   SYSOUT=A
//SYSTEM   DD   SYSOUT=A
//ASMAOPT  DD   DSN=PROG.OPTIONS,DISP=OLD
//SYSLIN   DD   DSN=PROG.OBJ,DISP=OLD
//SYSPUNCH DD   DSN=PROG.DECK,DISP=OLD
//SYSADATA DD   DSN=PROG.ADATA,DISP=OLD
//SYSIN    DD   DSN=PROG.SOURCE,DISP=SHR
```

Figure 33. JCL for assembly

Refer to “Bibliography” on page 451 for a list of JCL documents that describe additional techniques for specifying job control statements and overriding cataloged procedures.

## Invoking the assembler on TSO

On TSO, you can use TSO commands, command lists (CLISTs), REXX™ EXECs, or ISPF to assemble your program. Figure 34 shows how to allocate the data sets and assemble the source program using the **ALLOCATE** and **CALL** commands. The commands are shown in bold text.

```
READY
ALLOCATE FILE(SYSPRINT) DATASET(*) REUSE
READY
ALLOCATE FILE(SYSTEM) DATASET(*) REUSE
READY
ALLOCATE FILE(SYSLIN) DATASET(PROG.OBJ) NEW TRACKS SPACE(3,3)
      BLKSIZE(80) LRECL(80) RECFM(F B) CATALOG REUSE
READY
ALLOCATE FILE(SYSADATA) DATASET(PROG.ADATA) NEW CYLINDERS
      SPACE(1 1) BLKSIZE(32760) LRECL(32756) RECFM(V B)
      REUSE CATALOG
READY
ALLOCATE FILE(SYSIN) DATASET(PROG.ASSEMBLE) SHR REUSE
READY
ALLOCATE FILE(ASMAOPT) DATASET(PROG.OPTIONS) SHR REUSE
READY
CALL *(ASMA90) 'ADATA,LIST(133),OBJECT,TERM'
:
: Assembler listing and messages
:
READY
FREE FILE(SYSADATA,SYSPRINT,SYSTEM,SYSLIN,SYSIN)
READY
```

Figure 34. Assembling on TSO

You can enter **ALLOCATE** commands in any order; however, you must enter all of them before you start the assembly. Table 23 shows the data sets you must allocate when you specify particular assembler options.

Table 23. Assembler options and data sets required

Option Specified	Data Sets Required
Any	SYSUT1 and SYSIN
LIST	SYSPRINT
TERM	SYSTEM
OBJECT	SYSLIN
DECK	SYSPUNCH

## Invoking the assembler on TSO

Table 23. Assembler options and data sets required (continued)

Option Specified	Data Sets Required
ADATA	SYSADATA

**Exit Option:** If you specify the EXIT option, the user exit program module must be in a partitioned data set that is in the standard search sequence, including the Link Pack Area (LPA).

## Invoking the assembler dynamically

You can invoke High Level Assembler from a running program using the CALL, LINK, XCTL, or ATTACH system macro instructions.

**Note:** If the program that invokes the High Level Assembler is APF-authorized, then ensure that the High Level Assembler product resides in an Authorized Program Facility (APF) authorized library.

When you use CALL, LINK, or ATTACH, you can supply:

- The assembler options.
- The ddnames of the data sets to be used during processing.

If you use XCTL, you cannot pass options to the assembler. The assembler uses the installation default options. Table 24 shows how to invoke the assembler dynamically.

Table 24. Invoking the assembler dynamically

Name	Operation	Operand
<i>symbol</i>	CALL	▶▶ASMA90,( <i>optionlist</i> └┐,VL┐▶▶ └┐,ddnamelist┐
	LINK or ATTACH	▶▶EP=ASMA90,PARAM=( <i>optionlist</i> └┐,VL=1┐▶▶ └┐,ddnamelist┐

### ASMA90

The load module name and entry point to invoke the assembler. ASMA90 must be invoked in 31-bit addressing mode.

**EP** Specifies the symbolic name of the assembler load module and entry point.

### PARAM

Specifies, as a sublist, address parameters to be passed from the program to the assembler. The first word in the address parameter list (*optionlist*) contains the address of the option list. The second word (*ddnamelist*) contains the address of the ddname list.

#### *optionlist*

Specifies the address of a variable-length list containing the options. The address of an option list must be provided even if no options are required.

The option list must begin on a halfword boundary. The first two bytes contain the number of bytes in the remainder of the list. If no options are specified, the count must be zero. The option list is free form, with



each field separated from the next by a comma. No spaces should appear in the list, except within the string specified for the EXIT or SYSPARM options, providing the string is enclosed within single quotation marks.

### *ddnamelist*

Specifies the address of a variable-length list containing alternative ddnames for the data sets used during assembler processing. If standard ddnames are used, this operand can be omitted.

The ddname list must begin on a halfword boundary. The first two bytes contain the number of bytes in the remainder of the list. Each name of less than 8 bytes must be left-justified and padded to 8 bytes with spaces. If an alternative ddname is omitted, the standard name is assumed. If the name is omitted within the list, the 8-byte entry must contain binary zeros. Names can be omitted from the end merely by shortening the list. The sequence of the 8-byte entries in the ddname list is as follows:

Entry	Alternative
1	SYSLIN
2	Not applicable
3	Not applicable
4	SYSLIB
5	SYSIN
6	SYSPRINT
7	SYSPUNCH
8	SYSUT1
9	Not applicable
10	Not applicable
11	Not applicable
12	SYSTEM
13	Not applicable
14	Not applicable
15	Not applicable
16	SYSADATA
17	Not applicable
18	Not applicable
19	Not applicable
20	ASMAOPT

**Overriding ddname:** Any overriding ddname specified when High Level Assembler was installed, occupies the corresponding position in the above list. The overriding ddname can also be overridden during invocation. For example, if SYSWORK1 replaced SYSUT1, it occupies position 8 in the above list. However, SYSWORK1 can be overridden by another name during invocation.

**VL** specifies that the sign bit is to be set to 1 in the last word of the parameter address list. VL must be specified for the CALL macro and VL=1 for the LINK or ATTACH macros.

## Batch assembling

---

```
DYNAMICM CSECT
DYNAMICM RMODE 24
DYNAMICM AMODE ANY
BEGIN    SAVE    (14,12)
        USING    BEGIN,15
        ST       13,SAVEAREA+4
        LA       13,SAVEAREA
        CALL     ASMA90,(OPTIONS),VL
        L        13,SAVEAREA+4
        RETURN   (14,12)
SAVEAREA DS    18F
OPTIONS  DC     Y(OPTIONSL)
OPTS     DC     C'XREF(SHORT)'
OPTIONSL EQU    *-OPTS
END
```

---

*Figure 35. Sample program to call the assembler dynamically*

## Batch assembling

A sequence of separate assembler programs may be assembled with a single invocation of the assembler when the BATCH option is specified. The object programs produced from this assembly may be linked into either a single program module or separate program modules.

When the BATCH option is specified, each assembler program in the sequence must be terminated by an END statement, including the last program in the batch. If an END statement is omitted, the program will be assembled with the next program in the sequence. If the END statement is omitted from the last program in the sequence, an END statement will be generated by the assembler.

If you want to produce more than one program module, you must either separate the object modules, or write a NAME linkage editor control statement for each load module. The NAME statement must be written at the end of the object module. The following example shows how to create two program modules, SECT1 and SECT2.

```
SECT1    CSECT           Start of first load module
:
:           Source instructions
:
:           END           End of first load module
:           PUNCH ' NAME SECT1(R)'
:           END
SECT2    CSECT           Start of second load module
:
:           Source instructions
:
:           END           End of second load module
:           PUNCH ' NAME SECT2(R)'
:           END
```

## Input and output data sets

Depending on the options in effect, High Level Assembler requires the following data sets, as shown in Figure 36 on page 167:




Figure 36. High Level Assembler Files

You can override the ddnames during installation or when invoking the assembler dynamically (see “Invoking the assembler dynamically” on page 164).

High Level Assembler requires the following data set:

**SYSIN** An input data set containing the source statements to be processed.

In addition, the following seven data sets might be required:

**ASMAOPT** An input data set containing an assembler option list.

**SYSLIB** A data set containing macro definitions (for macro definitions not defined in the source program), source code to be called through COPY assembler instructions, or both.

**SYSPRINT** A data set containing the assembly listing (if the LIST option is in effect).

**SYSTEM** A data set containing a condensed form of SYSPRINT, principally flagged statements and their error messages (only if the TERM option is in effect).

**SYSPUNCH** A data set containing object module output (only if the DECK option is in effect).

**SYSLIN** A data set containing object module output usually for the linkage editor, loader, or binder (only if the OBJECT option is in effect).

**SYSADATA** A data set containing associated data output (only if the ADATA option is in effect).

The data sets listed above are described in “Specifying the source data set: SYSIN” on page 169. Table 25 describes the characteristics of these data sets, including the characteristics set by the assembler and those you can override. The standard ddname that defines the data set appears as the heading for each data set description.

Table 25. Assembler data set characteristics

Data Set	Access Method	Logical Record Length (LRECL)	Block Size (BLKSIZE)	Record Format (RECFM)
SYSIN	QSAM	80	<b>5</b>	<b>9</b>

## Input and output data sets

Table 25. Assembler data set characteristics (continued)

Data Set	Access Method	Logical Record Length (LRECL)	Block Size (BLKSIZE)	Record Format (RECFM)
ASMAOPT	QSAM	<b>12</b>	<b>7</b>	Fixed/Variable
SYSLIB	BPAM	80	<b>6</b>	<b>9</b>
SYSPRINT	QSAM	<b>1</b>	<b>7 8</b>	<b>10</b>
SYSTEM	QSAM	<b>2</b>	<b>5 8</b>	<b>11</b>
SYSPUNCH	QSAM	80	<b>5</b>	<b>4</b>
SYSLIN	QSAM	<b>3</b>	<b>5</b>	<b>4</b>
SYSADATA	QSAM	32756	32760 or greater <b>8</b>	VB

### Notes to Table 25:

- 1** If you specify EXIT(PRTEXT) and the user exit specifies the logical record length, the logical record length returned is used, unless the SYSPRINT data set has a variable-length record format in which case the LRECL used is 4 bytes greater than the value returned by the exit. If EXIT(PRTEXT) has not been specified or the user exit does not specify a record length, the record length from the DD statement or data set label is used if present. Otherwise, the record length defaults to 133, or 137 if the record format is variable-length.

The minimum record length allowed for SYSPRINT is 121, and the maximum allowed is 255. If the record format is variable-length, the LRECL should be at least 125 or 137 depending on the LIST option.

- 2** If you specify EXIT(TRMEXIT) and the user exit specifies the logical record length, the logical record length returned is used. If EXIT(TRMEXIT) has not been specified or the user exit does not specify a record length, the record length from the DD statement or data set label is used if present. If not present, the record length defaults to the record length for SYSPRINT (if the LIST option is in effect) or 133 otherwise.

The maximum record length allowed for SYSTEM is 255.

- 3** If you specify the OBJECT option the logical record length must be 80. If you specify the GOFF option the object module can be generated with either fixed-length records of 80 bytes, or variable-length records up to BLKSIZE of 32720.

**Hierarchical File System:** If you wish to copy the object data set to a file in a Hierarchical File System, for example under UNIX® System Services, the object data set must be created with fixed-length records.

- 4** Both fixed and variable formats are supported; the default is fixed.

- 5** If specified, the BLKSIZE must equal the LRECL or be a multiple of the LRECL. If BLKSIZE is not specified, it is set to LRECL.

Refer to the applicable *Linkage Editor and Loader* document, or *z/OS DFSMS Program Management*, for the block size requirements of SYSPUNCH and SYSLIN, if you use them as input to the linkage editor, or to the z/OS binder.

- 6** The BLKSIZE on the DD statement or the data set label must be equal to, or be a multiple of, the LRECL.

- 7** The blocksize must be equal to or a multiple of the record length if the record format is fixed. If the record format is variable the blocksize must be at least 4 bytes greater than the record length.
- 8** High Level Assembler supports z/OS System-Determined Blocksize (SDB) for all output data sets except SYSLIN and SYSPUNCH.

System-Determined Blocksize is applicable when all of the following conditions are true:

- The operating system is MVS/ESA with a MVS level of 3.1 or higher.
- The data set is NOT allocated to SYSOUT.
- A block size of zero is specified or the blocksize is not specified in the JCL.
- A record length (LRECL) is specified.
- A record format (RECFM) is specified.
- A data set organization (DSORG) is specified.

If these conditions are met, z/OS selects the appropriate blocksize for a new data set depending on the device type selected for output.

If the System-Determined Blocksize feature is not available, and your JCL omits the blocksize, or specifies a blocksize of zero, the assembler uses the logical record length as the blocksize.

- 9** Set by the assembler to F (or FB) if necessary.
- 10** Both fixed and variable formats are supported; the default is fixed. If the DD statement or data set label specifies machine or ASA control characters, the ASA option is set or reset accordingly. If machine or ASA control characters are not specified on the DD statement or data set label, the record format is modified according to the ASA option.
- 11** Set by the assembler to F (or FB) if necessary. The record format is set to FA (or FBA) if the ASA option is specified or FM (or FBM) otherwise.
- 12** The minimum record length allowed for ASMAOPT is 5 if the record format is variable-length or 1 if the record format is fixed-length. The maximum record length allowed is 32756 if the record format is variable length or 32760 if the record format is fixed-length.

## Specifying the source data set: SYSIN

Define the data sets that contain your source code with the SYSIN DD statement:

```
//SYSIN DD DSN=datasetname,DISP=SHR
```

This data set contains the input to the assembler; that is, the assembler language source statements to be processed.

You can place your assembler source code in the input stream. To do this, use this SYSIN DD statement:

```
//SYSIN DD *
```

When you use the (\*) DD parameter, the source code must follow the DD statement. If another job step follows the assembly, the EXEC statement for that step must follow the last source statement, or end-of-file (/\*) statement.

The IBM-supplied High Level Assembler procedures do not contain the SYSIN DD statement. The DD statement for SYSIN must be provided in the input stream:

## Input and output data sets

```
//STEP1    EXEC ASMAC
//SYSIN    DD    *
:
:
: assembler source statements
:
:
/*
```

### Specifying the option file: ASMAOPT

Define the data set that contains the options with the ASMAOPT DD statement:

```
//ASMAOPT DD    DSN=datasetname,DISP=SHR
```

This data set contains the option list for the assembler.

### Specifying macro and copy code libraries: SYSLIB

Define the partitioned data sets that contain your macro or copy members with the SYSLIB DD statement:

```
//SYSLIB    DD    DSN=SYS1.MACLIB,DISP=SHR
```

From this data set, the assembler obtains macro definitions and assembler language statements to be called by the COPY assembler instruction. Each macro definition or sequence of assembler language statements is a separate member in a partitioned data set. The member name is the operation code used to invoke the macro in a macro instruction, or the operand name in a COPY instruction.

The data set can be defined as SYS1.MACLIB, or your private macro definition or COPY library. SYS1.MACLIB contains macro definitions for the system macro instructions provided by IBM. Your private library may be concatenated with SYS1.MACLIB. The two libraries must have the same logical record length (80 bytes), but the blocking factors may be different. The applicable *JCL Reference* explains the concatenation of data sets.

### Specifying the listing data set: SYSPRINT

Define the data set that contains your listing output with the SYSPRINT DD statement:

```
//SYSPRINT DD    SYSOUT=A
```

The assembler uses this data set to produce a listing. You can direct output to a printer, a magnetic tape, or a direct-access storage device. The assembler uses ASA or machine control characters for this data set according to the ASA option.

### Directing assembler messages to your terminal: SYSTEM

Define the data set that contains your terminal message's output with the SYSTEM DD statement:

```
//SYSTEM DD    SYSOUT=A
```

On TSO, the terminal messages can be sent to your terminal by using the following ALLOC statement:

```
ALLOC F(SYSTEM) DA(*)
```

This data set is used by the assembler to store a condensed form of SYSPRINT containing flagged statements and their associated error messages. It is intended for output to a terminal, but can also be routed to a printer, a magnetic tape, or a direct-access storage device. Depending on the ASA option, the assembler uses ASA or machine control characters to skip to a new line for this data set.

## Specifying object code data sets: SYSLIN and SYSPUNCH

Define the data set that contains your object output with the SYSLIN and SYSPUNCH DD statements. When the OBJECT option is in effect, the object module is written to SYSLIN. When the DECK option is in effect, the object module is written to SYSPUNCH. When both OBJECT and DECK options are in effect, the object module is written to both SYSLIN and SYSPUNCH.

You can direct the SYSLIN data set to either a card punch or an intermediate storage device capable of sequential access:

```
//SYSLIN DD DSN=dsname,UNIT=SYSALLDA,
//          SPACE=(subparms),DISP=(MOD,PASS)
```

You can direct the SYSPUNCH data set to either a card punch or an intermediate storage device capable of sequential access:

```
//SYSPUNCH DD SYSOUT=B
```

## Specifying the associated data data set: SYSADATA

Define the data set that contains your associated data output with the SYSADATA DD statement:

```
//SYSADATA DD DSN=dsname,UNIT=SYSALLDA,
//           SPACE=(subparms),DISP=(MOD,PASS)
```

The associated data data set contains information regarding the assembly. It provides information for use by symbolic debugging and cross-reference tools. The SYSADATA data set must be directed to an intermediate storage device capable of sequential access.

---

## Return codes

High Level Assembler issues return codes for use with the IF job control statement and the COND parameter of the JOB and EXEC job control language statements. The IF statement and the COND parameter enable you to skip or to run a job step, depending on the results (indicated by the return code) of a previous job step. It is explained in the applicable *JCL Reference*.

The return code issued by the assembler is the highest severity code that is associated with any error detected in the assembly or with any MNOTE message produced by the source program or macro instructions. The return code can be controlled by the FLAG(*n*) assembler option described on page 54. See Appendix G, “High Level Assembler messages,” on page 335 for a listing of the assembler errors and their severity codes.





---

## Chapter 8. Linking and running your program on z/OS

The output from an assembly is an *object module*. An object module is a relocatable module of machine code that is not executable.

Before an object module can be executed, you must use the binder to convert it into executable machine code.

---

### The program management binder

The binder converts object modules into an executable program unit that can either be read directly into virtual storage for execution, or stored in a program library. Executable program units can either be load modules, or *program objects*. You can use the binder to:


- Convert object or load modules, or program objects, into a program object and store it in a PDSE program library.
- Convert object or load modules, or program objects, into a load module and store it in a partitioned data set program library.
- Convert object or load modules, or program objects, into an executable program in virtual storage and execute the program.

For the remainder of this section, the binder is referred to as the *binder*, unless otherwise stated.

For more information, see the *z/OS MVS Program Management: User's Guide and Reference*.

## The loader

---



Components are shown in uppercase.

↔ = Two-way relationship.  
Indicates a component can  
produce that structure as  
output or accept it as input.

---

Figure 37. Using the program management components

---

## The loader

The loader component of z/OS, and the batch loader component of z/OS perform the same task. Given this, the batch loader is hereafter referred to as the *loader*, unless otherwise stated.

The loader combines the basic editing and loading services, that can also be provided by the binder and program fetch, into one step. The loader accepts object modules and load modules, and loads them into virtual storage for execution. The loader does not produce load modules that can be stored in program libraries.

To keep a load module for later execution, use the binder.

## Creating a load module

The binder processes your object module (assembled source program) and prepares it for execution. The processed object module becomes a load module or program object.

Optionally, the binder can process more than one object module, or load module, or program object, and convert them into one or more load modules, or program objects, by using the NAME control statement. See “Batch assembling” on page 166 for an example that uses the NAME control statement.

## Creating a load module on z/OS

Figure 38 shows the general job control for creating a load module or program object.

```
//jobname JOB acctno,name,MSGLEVEL=1
:
//stepname EXEC PGM=HEWL,PARM=(options)
//SYSPRINT DD SYSOUT=A
//SYSLMOD DD DSN=&&name(member),UNIT=SYSALLDA,
// DISP=(NEW,PASS),SPACE=(subparms)
//SYSLIB DD DSN=dsname,DISP=SHR
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSLIN DD DSN=MYOBJ,DISP=SHR
```

Figure 38. Sample job control for creating a load module

High Level Assembler provides cataloged procedures for the following:

- Assembly and link.
- Assembly, link, and go (to execute your program).
- Assembly and go using the loader.

See “Using cataloged procedures” on page 184.

## Creating a load module on TSO

You can invoke the binder on TSO (Time Sharing Option) with the LINK and LOADGO commands.

The LINK command creates a load module and saves it in a PDS or it creates a program object and saves that in a PDSE.

The LOADGO command creates and executes a program module. The module is not saved in a program library.

### Examples using the LINK command

If your assembly produced an object module in a data set called PROGRAM1.OBJ, issue the following LINK command at your terminal:

```
LINK PROGRAM1
```

The program module is placed by default in member TEMPNAME of a partitioned data set, or PDSE program library called *userid*.PROGRAM1.LOAD. If you want to put the program module in a different data set, issue the following LINK command:

## Creating a load module

```
LINK PROGRAM1 LOAD(data-set-name(member-name))
```

where *data-set-name* is a program library, and *member-name* is the name of the program module.

The following example shows how to link two object modules and place the resulting program module in member TEMPNAME of the *userid*.LM.LOAD data set:

```
LINK PROGRAM1,PROGRAM2 LOAD(LM)
```

If your program refers to other modules (that is, external references), you can instruct the binder to search for them by including the LIB parameter on the LINK command. The LIB parameter specifies one or more names of library data sets to search. For example:

```
LINK PROGRAM1 LIB('SALESLIB.LIB.SUBRT2')
```

This request searches library SALESLIB.LIB.SUBRT2.

You can also specify link options on the LINK and LOADGO commands. See “Specifying binder options using the TSO LINK command” on page 180.

Binder options are discussed in “Binder processing options” on page 178.

For more information about using the LINK and LOADGO commands, see the *z/OS TSO/E Command Reference*.

---

## Input to the binder

Your input to the binder can be:

- One or more object modules.
- Binder control statements (that you can generate using the PUNCH assembler statement).
- Previously linked program modules you want to combine into one load module.

The *primary* input to the binder can be:

- A sequential data set.
- A member of a partitioned data set.
- A member of a PDSE (if you are using the binder to link your program).
- Concatenated data sets of any combination of the above.

The primary input data set can contain object modules, binder control statements, and linked program modules.

You specify the primary input data set with the SYSLIN DD statement.

*Secondary* input to the binder can consist of object modules or program modules that are not part of the primary input data set, but are included explicitly or automatically in the program module using the *automatic call library* process.

An automatic call library contains modules that you can use as secondary input to the binder to resolve external symbols left undefined after all primary input has been processed.

The automatic call library may be in the form of:

- Libraries containing object modules, with or without binder control statements.
- Libraries containing linked program modules.

Secondary input for the binder is composed of either all object modules or all load modules, but it cannot contain both types. Secondary input for the binder can be any combination of object modules, load modules libraries, and program object libraries.

You specify the secondary input data sets with a SYSLIB DD statement and, if the data sets are object modules, the LIBRARY and INCLUDE control statements. If you have multiple secondary input data sets, concatenate them as follows:

```
//SYSLIB DD DSN=ORDERLIB,DISP=SHR
//          DD DSN=SAESLIB,DISP=SHR
```

In this case, both the partitioned data sets (library) named ORDERLIB and SAESLIB are available as the automatic call library. The LIBRARY control statement has the effect of concatenating any specified member names with the automatic call library.

## Data sets for binder processing

You need the following data sets for binder processing. Others may be necessary if you have several additional libraries or object modules. If you need additional libraries and object modules, include a DD statement for them in your JCL. Table 26 summarizes the data sets that you need for linking.

*Table 26. Data sets used for linking*

DD name	Type	Function
SYSLIN <sup>1</sup>	Input	Primary input data, normally the output of the assembler
SYSPRINT <sup>1</sup>	Output	Diagnostic messages Informative messages Module map Cross reference list
SYSLMOD <sup>1</sup>	Output	Output data set for the program module
SYSLUT <sup>1</sup>	Utility	Work data set. Not used by the binder.
SYSLIB	Library	Automatic call library
SYSTEM <sup>2</sup>	Output	Numbered error or warning messages
User specified <sup>3</sup>		Additional object modules and program modules

### Notes:

- <sup>1</sup> Required data set
- <sup>2</sup> Required if TERM option is specified
- <sup>3</sup> Optional data set

## Additional object modules as input

You can use the INCLUDE and LIBRARY control statements to:

1. Specify additional object modules you want included in the program module (INCLUDE statement).
2. Specify additional libraries to search for object modules to include in the program module (LIBRARY statement). This statement has the effect of concatenating any specified member names with the automatic call library.

## Input to the binder

Figure 39 shows an example that uses the INCLUDE and LIBRARY control statements.

```
⋮
//SYSLIN DD DSNAME=&&GOFIL,DISP=(SHR,DELETE)
// DD *
INCLUDE MYLIB(ASMLIB,ASSMPGM)
LIBRARY ADDLIB(COBREGN0)
/*
```

Figure 39. INCLUDE and LIBRARY control statements

Data sets you specify on the INCLUDE statement are processed as the binder encounters the statement. In contrast, data sets you specify on the LIBRARY statement are used only when there are unresolved references after all the other input is processed.

For more information, see the *z/OS MVS Program Management: User's Guide and Reference*.

## Output from the binder

SYSLMOD and SYSPRINT are the data sets used for binder output. The output varies depending on the options you select, as shown in Table 27.

Table 27. Options for controlling binder output

To Get This Output	Use This Option
A map of the program modules generated by the binder.	MAP
A cross-reference list of data variables	XREF
Informative messages	Default
Diagnostic messages	Default
Listing of the binder control statements	LIST
One or more program modules (which you must assign to a library)	Default

You always receive diagnostic and informative messages as the result of linking. You can get the other output items by specifying options in the PARM parameter of the EXEC statement in your JCL.

The program modules are written to the data set defined by the SYSLMOD DD statement in your JCL. Diagnostic output is written to the data set defined by the SYSPRINT DD statement.

## Binder processing options

Binder options can be specified in one of these ways:

- In your JCL.
- When you invoke the LINK or LOADGO command on TSO.

Table 28 on page 179 describes some of these options.

Table 28. Link processing options

Option	Action	Comments
LET	Lets you specify the severity level of an error, to control whether the binder marks the program module as non-executable.	The LET option is used differently between the linkage editor and the binder.
MAP NOMAP	Use MAP if you want to get a map of the generated program modules. NOMAP suppresses this map listing.	The map of the program module gives the length and location (absolute addresses) of the main program and all subprograms. NOMAP is the default.
NCAL	When you use the no automatic library call option (NCAL), the binder does not search for library members to resolve external references.	If you specify NCAL, you don't need to use the LIBRARY statement, and you don't need to supply the SYSLIB DD statement.
RENT NORENT	The RENT option indicates to the binder that the object module is reenterable and can be used by more than one task at a time. This type of module cannot be modified by itself or any other module when it is running. The assembler RENT option can be used to assist in determining whether the object module is reentrant. NORENT indicates that the object module is not reentrant.	The assembler RENT option and binder RENT option are independent of each other. NORENT is the default binder option.
AMODE 24   31   ANY	Use AMODE (addressing mode) to override the default AMODE attribute established by the assembler.	See "AMODE and RMODE attributes" on page 180.
RMODE 24   ANY	Use RMODE (residence mode) to override the default RMODE attribute established by the assembler.	See "AMODE and RMODE attributes" on page 180.
PRINT	When you use the TSO commands LINK or LOADGO, the PRINT option specifies where to print diagnostic messages and the module map.  PRINT is also an option of the loader, and controls whether diagnostic messages are produced.	See also "Specifying binder options using the TSO LINK command" on page 180.

## Specifying binder options through JCL

In your link JCL, use the PARM statement to specify options:

```
PARM=(binder-options)
PARM.stepname=('binder-options')
```

*binder-options*

A list of binder options (see Table 28). Separate the options with commas.

*stepname*

The name of the step in the cataloged procedure that contains the PARM statement.

Figure 40 on page 180 shows the job control to pass PARM.C and PARM.L options.

---

```

/* ASSEMBLE USING ASMACL
//      JCLLIB ORDER=(ASM.SASMSAM1)
//HLASM EXEC ASMACL,PARM.C='NODECK,OBJ',
//      PARM.L='LIST,LET,XREF,MAP'
//STEPLIB DD DISP=SHR,DSN=ASM.SASMMOD1
//C.SYSIN DD *
//      BR 14      < ASSEMBLER PROGRAM GOES HERE
//      END
/*

```

---

Figure 40. Job control to pass PARM.C and PARM.L options

For more information, see the *HLASM Installation and Customization Guide*.

## Specifying binder options using the TSO LINK command

You specify binder options on the LINK and LOADGO commands. The following example shows you how to specify the LET, MAP, and NOCALL options when you issue the LINK command:

```
LINK PROGRAM1 LET MAP NOCALL
```

You can use the PRINT option to display the module map at your terminal:

```
LINK PROGRAM1 MAP PRINT(*)
```

The \* indicates that the output from the binder is displayed at your terminal. NOPRINT suppresses any messages.

## AMODE and RMODE attributes

Every program that runs in z/OS is assigned two attributes, an AMODE (addressing mode) and an RMODE (residency mode):

**AMODE** Specifies the addressing mode in which the program is designed to receive control. Generally, the program is also designed to run in that mode, although a program can switch modes and can have different AMODE attributes for different entry points within a program module.

z/OS uses a program's AMODE attribute to determine whether a program invoked using ATTACH, LINK, or XCTL is to receive control in 24-bit or 31-bit addressing mode.

**RMODE** Indicates where the program can reside in virtual storage.

z/OS uses the RMODE attribute to determine whether a program must be loaded into virtual storage below 16 megabytes, or can reside anywhere in virtual storage (above or below 16 megabytes).

Valid AMODE and RMODE specifications are:

Attribute	Meaning
AMODE=24	24-bit addressing mode
AMODE=31	31-bit addressing mode
AMODE=64	64-bit addressing mode
AMODE=ANY	Either 24-bit or 31-bit addressing mode
RMODE=24	The module must reside in virtual storage below 16 megabytes. Use RMODE=24 for programs that have 24-bit dependencies.



Attribute	Meaning
RMODE=ANY	Indicates that the module can reside anywhere in storage, which includes addresses above the 16 megabyte line.

If you don't specify the AMODE or RMODE in the assembler program or when you link the program, both AMODE and RMODE default to 24.

## Overriding the defaults

The following examples show you how to override the default AMODE and RMODE values:

- Using the EXEC JCL statement:
  - `//LKED EXEC PGM=IEWBLINK,`
  - `// PARM='AMODE=31,RMODE=ANY'`
- Using the TSO commands LINK or LOADGO:
  - `LINK PROGRAM1 AMODE(31) RMODE(ANY)`
  - `LOADGO PROGRAM1 AMODE(31) RMODE(ANY)`

You can also use binder control statements to override the default AMODE and RMODE values.

## Detecting binder errors

The binder produces a listing in the data set defined by the SYSPRINT DD statement. The listing includes any informational or diagnostic messages issued by the binder. You should check the load map to make sure that all the modules you expected were included.

For more information, see the *z/OS MVS Program Management: User's Guide and Reference*.

## Running your assembled program

When you've completed the preparatory work for your assembler program (designing, coding, assembling, and linking), the program is ready to run.

You can use cataloged procedures to combine the assemble, link, and go procedures in your programs. See "Using cataloged procedures" on page 184.

## Running your assembled program in batch

Figure 41 shows the general job control to run your program in batch.

---

```
//stepname EXEC PGM=programe[,PARM='user-parameters']
//STEPLIB DD DSN=library.dsname,DISP=SHR
//ddname DD (parameters for user-specified data sets)
:
```

---

Figure 41. General job control to run a program on z/OS

For more information, see the *HLASM Installation and Customization Guide*.

### Running your assembled program on TSO

You use the CALL command to run your program on TSO, as follows:

```
CALL 'JRL.LIB.LOAD(PROGRAM1)'
```

If you omit the descriptive qualifier (LOAD) and the member name (PROGRAM1), the system assumes LOAD and TEMPNAME, respectively. If your program module is in the data set JRL.LIB.LOAD(TEMPNAME), and your TSO userid is JRL, enter:

```
CALL LIB
```

---

## Chapter 9. z/OS system services and programming considerations

This chapter describes some of the z/OS system services and program development facilities that assist you in developing your assembler program. It provides the following information:

- Adding definitions to a macro library.
- Using cataloged procedures.
- Overriding statements in cataloged procedures.
- Saving and restoring general register contents.
- Ending program execution.
- Accessing execution parameters.
- Combining object modules to form a single program module.
- Modifying program modules.

---

### Adding definitions to a macro library

You can add macro definitions, and members containing assembler source statements that can be read by a COPY instruction, to a macro library. You can use the system utility IEBUPDTE for this purpose. You can find the details of IEBUPDTE and its control statements in *z/OS DFSMSdfp Utilities*.

Figure 42 shows how a new macro definition, NEWMAC, is added to the system library, SYS1.MACLIB.

---

//CATMAC	JOB	1,MSGLEVEL=1	
//STEP1	EXEC	PGM=IEBUPDTE,PARM=MOD	
//SYSUT1	DD	DSNAME=SYS1.MACLIB,DISP=OLD	1
//SYSUT2	DD	DSNAME=SYS1.MACLIB,DISP=OLD	1
//SYSPRINT	DD	SYSOUT=A	2
//SYSIN	DD	DATA	
./	ADD	LIST=ALL,NAME=NEWMAC,LEVEL=01,SOURCE=0	3
	MACRO		4
	NEWMAC	&OP1,&OP2	
	LCLA	&PAR1,&PAR2	
:			
	MEND		
./	ENDUP		
/*			

---

Figure 42. Macro library addition procedure

#### Notes to Figure 42:

- 1** The SYSUT1 and SYSUT2 DD statements indicate that SYS1.MACLIB, an existing program library, is to be updated.
- 2** Output from the IEBUPDTE program is printed on the Class A output device (specified by SYSPRINT).
- 3** The utility control statement, ./ ADD, and the macro definition follow the SYSIN statement. The ./ ADD statement specifies that the statements following it are to be added to the macro library under the name NEWMAC. When you include macro definitions in the library, the name

## Adding definitions to a macro library

specified in the NAME parameter of the `./ ADD` statement must be the same as the operation code of the prototype statement of the macro definition.

- 4** Following the ADD utility control statement is the macro definition itself.

---

## Using cataloged procedures

Often you use the same set of job control statements repeatedly; for example, to specify the assembly, linking, and running of many different programs. To save programming time and to reduce the possibility of error, standard sets of EXEC and DD statements can be prepared once and cataloged in a procedure library. Such a set of statements is termed a *cataloged procedure* and can be invoked by either of the following statements:

```
//stepname EXEC procname  
//stepname EXEC PROC=procname
```

The specified procedure (*procname*) is read from the procedure library (SYS1.PROCLIB) and merged with the job control statements that follow this EXEC statement.

This section describes four IBM cataloged procedures: a procedure for assembling (ASMAC); a procedure for assembling and linking (ASMACL); a procedure for assembling, linking, and running (ASMACLG); and a procedure for assembling and running the loader (ASMACG).

### Cataloged procedure for assembly (ASMAC)

This procedure consists of one job step: assembly. Use the name ASMAC to call this procedure. The result of running this procedure is an object module written to SYSPUNCH and an assembler listing. (See “Invoking the assembler on z/OS” on page 161 for more details and another example.)

In the following example, input is provided in the input stream:

```
//jobname JOB  
//stepname EXEC PROC=ASMAC  
//SYSIN DD *  
:  
:  
assembler source statements  
:  
/* (delimiter statement)
```

The statements of the ASMAC procedure are read from the procedure library and merged into the input stream.

Figure 43 on page 185 shows the statements that make up the ASMAC procedure.

```

//ASMAC    PROC
//*
//*****
//*    Licensed Materials - Property of IBM                *
//*                                                    *
//*    5696-234    5647-A01                              *
//*                                                    *
//*    (C) Copyright IBM Corp. 1992, 2008. All Rights Reserved. *
//*                                                    *
//*    US Government Users Restricted Rights - Use,      *
//*    duplication or disclosure restricted by GSA ADP    *
//*    Schedule Contract with IBM Corp.                  *
//*                                                    *
//*****
//*    ASMAC                                              *
//*                                                    *
//*    THIS PROCEDURE RUNS THE HIGH LEVEL ASSEMBLER AND CAN BE USED *
//*    TO ASSEMBLE PROGRAMS.                              *
//*                                                    *
//*****
//C          EXEC PGM=ASMA90
//SYSLIB     DD  DSN=SYS1.MACLIB,DISP=SHR
//SYSUT1     DD  DSN=&&SYSUT1,SPACE=(4096,(120,120),,,ROUND),
//              UNIT=SYSALLDA,DCB=BUFNO=1
//SYSPRINT   DD  SYSOUT=*
//SYSLIN     DD  DSN=&&OBJ,SPACE=(3040,(40,40),,,ROUND),
//              UNIT=SYSALLDA,DISP=(MOD,PASS),
//              DCB=(BLKSIZE=3040,LRECL=80,RECFM=FB,BUFNO=1)

```

1  
2  
3  
4

Figure 43. Cataloged procedure for assembly (ASMAC)

#### Notes to Figure 43:

- 1** This statement identifies the macro library data set. The data set name SYS1.MACLIB is an IBM designation.
- 2** This statement specifies the assembler work data set. The device class name used here, SYSALLDA, represents a direct-access unit. The I/O unit assigned to this name is specified by the installation when the operating system is generated. A unit name such as 3390 or SYSDA can be substituted for SYSALLDA.
- 3** This statement defines the standard system output class, SYSOUT=\*, as the destination for the assembler listing.
- 4** This statement describes the data set that contains the object module produced by the assembler.

### Cataloged procedure for assembly and link (ASMACL)

This procedure consists of two job steps: assembly and link. Use the name ASMACL to call this procedure. This procedure produces an assembler listing, the binder listing, and a program module.

The following example shows input to the assembler in the input job stream. SYSLIN contains the output from the assembly step and the input to the link step. It can be concatenated with additional input to the binder as shown in the example. This additional input can be binder control statements or other object modules.

An example of the statements entered in the input stream to use this procedure is:

## Using cataloged procedures

```
//jobname          JOB
//stepname         EXEC PROC=ASMACL
//C.SYSIN          DD  *
:
:
: assembler source statements
:
:
: /*
:
: //L.SYSIN         DD  *
:
:
: object module or binder control statements
: /*
```

//L.SYSIN is necessary only if the binder is to combine modules or read editor control information from the job stream.

Figure 44 shows the statements that make up the ASMACL procedure. Only those statements not previously discussed are explained in the figure.

```

//ASMACL      PROC
//*
//*****
//*   Licensed Materials - Property of IBM
//*
//*   5696-234    5647-A01
//*
//*   (C) Copyright IBM Corp. 1992, 2008. All Rights Reserved.
//*
//*   US Government Users Restricted Rights - Use,
//*   duplication or disclosure restricted by GSA ADP
//*   Schedule Contract with IBM Corp.
//*
//*****
//*
//*   ASMACL
//*
//*
//* THIS PROCEDURE RUNS THE HIGH LEVEL ASSEMBLER, LINK-EDITS THE
//* NEWLY ASSEMBLED PROGRAM.
//*
//*****
//*
//C          EXEC PGM=ASMA90
//SYSLIB    DD  DSN=SYS1.MACLIB,DISP=SHR
//SYSUT1    DD  DSN=SYS1.SYSUT1,SPACE=(4096,(120,120),,,ROUND),
//           UNIT=SYSALLDA,DCB=BUFNO=1
//SYSPRINT  DD  SYSOUT=*
//SYSLIN    DD  DSN=SYS1.SYSUT1,SPACE=(4096,(120,120),,,ROUND),
//           UNIT=SYSALLDA,DISP=(MOD,PASS),
//           DCB=(BLKSIZE=3040,LRECL=80,RECFM=FB,BUFNO=1)
//L          EXEC PGM=HEWL,PARM='MAP,LET,LIST,NCAL',COND=(8,LT,C)
//SYSLIN    DD  DSN=SYS1.SYSUT1,DISP=(OLD,DELETE)
//           DD  DDNAME=SYSIN
//SYSLMOD    DD  DISP=(,PASS),UNIT=SYSALLDA,SPACE=(CYL,(1,1,1)),
//           DSN=SYS1.SYSUT1,DISP=(MOD,PASS),
//           DCB=(BLKSIZE=3040,LRECL=80,RECFM=FB,BUFNO=1)
//SYSUT1    DD  DSN=SYS1.SYSUT1,SPACE=(1024,(120,120),,,ROUND),
//           UNIT=SYSALLDA,DCB=BUFNO=1
//SYSPRINT  DD  SYSOUT=*

```

Figure 44. Cataloged procedure for assembling and linking (ASMACL)

### Notes to Figure 44:

- 1** In this procedure, the SYSLIN DD statement describes a temporary data set, the object module, which is passed to the binder.
- 2** This statement runs the binder. The binder options in the PARM field cause the binder to produce a cross-reference table, a module map, and a list of all control statements processed by the binder. The NCAL option suppresses the automatic library call function of the binder.
- 3** This statement identifies the binder input data set as the same one (SYSLIN) produced as output from the assembler.
- 4** This statement is used to concatenate any input to the binder from the input stream (object decks, binder control statements, or both) with the input from the assembler.
- 5** This statement specifies the binder output data set (the program load module). As specified, the data set is deleted at the end of the job. If it is required to retain the program module, the DSN parameter must be respecified and a DISP parameter added. See “Overriding statements in cataloged procedures” on page 190. If you want to retain the output of the binder, the DSN parameter must specify a library name and a member name at which the program module is to be placed. The DISP parameter must specify either KEEP or CATLG.
- 6** This statement specifies the work data set for the binder.
- 7** This statement identifies the standard output class as the destination for the binder listing.

## Cataloged procedure for assembly, link, and run (ASMACLG)

This procedure consists of three job steps: assembly, link, and run. Use the name ASMACLG to call this procedure. It produces an assembler listing, an object module, and a binder listing.

The statements entered in the input stream to use this procedure are:

```
//jobname          JOB
//stepname          EXEC PROC=ASMACLG
//C.SYSIN           DD  *
:
:
: assembler source statements
:
/*
//L.SYSIN           DD  *
:
: object module or binder control statements
:
/*
//G.ddname          DD   (parameters)
//G.ddname          DD   (parameters)
//G.ddname          DD   *
:
: program input
:
/*
```

//L.SYSIN is necessary only if the binder is to combine modules or read binder control information from the job stream.

//G.ddname statements are included only if necessary.

## Using cataloged procedures

Figure 45 shows the statements that make up the ASMACLG procedure. Only those statements not previously discussed are explained in the figure.

```
//ASMACLG PROC
//*
//*****
//* Licensed Materials - Property of IBM *
//* *
//* 5696-234 5647-A01 *
//* *
//* (C) Copyright IBM Corp. 1992, 2008. All Rights Reserved. *
//* *
//* US Government Users Restricted Rights - Use, *
//* duplication or disclosure restricted by GSA ADP *
//* Schedule Contract with IBM Corp. *
//* *
//*****
//* ASMACLG *
//* *
//* THIS PROCEDURE RUNS THE HIGH LEVEL ASSEMBLER, LINK-EDITS THE *
//* NEWLY ASSEMBLED PROGRAM AND RUNS THE PROGRAM AFTER *
//* THE LINK-EDIT IS ACCOMPLISHED. *
//* *
//*****
//*
//C EXEC PGM=ASMA90
//SYSLIB DD DSN=SYS1.MACLIB,DISP=SHR
//SYSUT1 DD DSN=&&SYSUT1,SPACE=(4096,(120,120),,ROUND),
// UNIT=SYSALLDA,DCB=BUFNO=1
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DSN=&&OBJ,SPACE=(3040,(40,40),,ROUND),
// UNIT=SYSALLDA,DISP=(MOD,PASS),
// DCB=(BLKSIZE=3040,LRECL=80,RECFM=FB,BUFNO=1)
I //L EXEC PGM=HEWL,PARM='MAP,LET,LIST',COND=(8,LT,C) 1
//SYSLIN DD DSN=&&OBJ,DISP=(OLD,DELETE)
// DD DDNAME=SYSIN
//SYSLMOD DD DISP=(,PASS),UNIT=SYSALLDA,SPACE=(CYL,(1,1,1)), 2
// DSN=&&GOSET(GO)
//SYSUT1 DD DSN=&&SYSUT1,SPACE=(1024,(120,120),,ROUND),
// UNIT=SYSALLDA,DCB=BUFNO=1
//SYSPRINT DD SYSOUT=*
//G EXEC PGM=*.L.SYSLMOD,COND=((8,LT,C),(8,LT,L)) 3
```

Figure 45. Cataloged procedure for assembly, link, and run (ASMACLG)

### Notes to Figure 45:

- 1** The LET binder option specified in this statement causes the binder to mark the program module as executable, even if errors are encountered during processing.
- 2** The output of the binder is specified as a member of a temporary data set, residing on a direct-access device, and is to be passed to a following job step.
- 3** This statement runs the assembled and binder program. The notation \*.L.SYSLMOD identifies the program to be run as being in the data set described in job step L by the DD statement named SYSLMOD.



## Cataloged procedure for assembly and run (ASMACG)

This procedure consists of two job steps: assembly and run, using the loader. Program modules for program libraries are not produced.

Enter these statements in the input stream to use this procedure:

```
//jobname      JOB
//stepname     EXEC PROC=ASMACG
//C.SYSIN      DD  *
:
:
: assembler source statements
:
:
/*
//G.ddname      DD  (parameters)
//G.ddname      DD  (parameters)
//G.ddname      DD  *
:
:
: program input
:
:
/*
```

//G.ddname statements are included only if necessary.

Figure 46 on page 190 shows the statements that make up the ASMACG procedure. Only those statements not previously discussed are explained in the figure.

Use the name ASMACG to call this procedure. Assembler and loader listings are produced. See Figure 46 on page 190.

```
//ASMACG  PROC
//*
//*****
//*  Licensed Materials - Property of IBM
//*
//*  5696-234    5647-A01
//*
//*  (C) Copyright IBM Corp. 1992, 2008. All Rights Reserved.
//*
//*  US Government Users Restricted Rights - Use,
//*  duplication or disclosure restricted by GSA ADP
//*  Schedule Contract with IBM Corp.
//*
//*****
//*
//*  ASMACG
//*
//*  THIS PROCEDURE RUNS THE HIGH LEVEL ASSEMBLER AND WILL USE
//*  THE LOADER PROGRAM TO RUN THE NEWLY ASSEMBLED PROGRAM.
//*
//*****
//*
//C      EXEC PGM=ASMA90
//SYSLIB DD DSN=SYS1.MACLIB,DISP=SHR
//SYSUT1 DD DSN=&&SYSUT1,SPACE=(4096,(120,120),,,ROUND),
//        UNIT=SYSALLDA,DCB=BUFNO=1
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DSN=&&OBJ,SPACE=(3040,(40,40),,,ROUND),
//        UNIT=SYSALLDA,DISP=(MOD,PASS),
//        DCB=(BLKSIZE=3040,LRECL=80,RECFM=FB,BUFNO=1)
//G      EXEC PGM=LOADER,PARM='MAP,LET,PRINT',COND=(8,LT,C)
//SYSLIN DD DSN=&&OBJ,DISP=(OLD,DELETE)
//        DD DDNAME=SYSIN
//SYSLOUT DD SYSOUT=*
```

**1**  
**2**

**3**

Figure 46. Cataloged procedure for assembly and running using the loader (ASMACG)

### Notes to Figure 46:

- 1** This statement runs the loader. The loader options in the PARM field cause the loader to produce a map and print the map and diagnostics. The NOCALL option is the same as NCAL for the binder, and the LET option is the same as for the binder.
- 2** This statement defines the loader input data set as the same one produced as output by the assembler.
- 3** This statement identifies the standard output class as the destination for the loader listing.

## Overriding statements in cataloged procedures

You can override any parameter in a cataloged procedure except the PGM= parameter in the EXEC statement. Overriding of statements or fields is effective only for the duration of the job step in which the statements appear. The statements, as stored in the procedure library of the system, remain unchanged.

To respecify, add, or nullify statements, include statements in the input stream that contain the required changes and identify the statements to be overridden.

## EXEC statements

Any EXEC parameter (except PGM) can be overridden. For example, the PARM= and COND= parameters can be added or, if present, respecified by including them in the EXEC statement calling the procedure. The JCL notation to specify these parameters is:

```
//ASM EXEC   PROC=ASMACLG,PARM.C=(NOBJECT),COND.L=(8,LT,stepname.c)
```

*stepname* identifies the EXEC statement within the catalogued procedure (ASMACLG) to which the modification applies.

If the procedure consists of more than one job step, a PARM.procstepname= or COND.procstepname= parameter can be entered for each step. The entries must be in order (PARM.procstepname1=, PARM.procstepname2=, ...).

## DD statements

All parameters in the operand field of DD statements can be overridden by including in the input stream (following the EXEC statement calling the procedure) a DD statement with the notation *//procstepname.ddname* in the name field. *procstepname* refers to the job step in which the statement identified by *ddname* appears.

If more than one DD statement in a procedure is to be overridden, the overriding statements must be in the same order as the statements in the procedure.

## Examples of cataloged procedures

1. In the assembly procedure ASMAC (Figure 43 on page 185), you might want to suppress the object module to SYSPUNCH and respecify the UNIT= and SPACE= parameters of data set SYSUT1. In this case, the following statements are required:

```
//stepname   EXEC   PROC=ASMAC,
//           PARM=NODECK
//SYSUT1     DD     UNIT=3390,
//           SPACE=(4096,(300,40))
//SYSIN      DD     *
:
: assembler source statements
:
/*
```

2. In procedure ASMACLG (Figure 45 on page 188), you might want to suppress the assembler listing, and add the COND= parameter to the EXEC statement that invokes the binder. In this case, the EXEC statement in the input stream are:

```
//stepname   EXEC   PROC=ASMACLG,
//           PARM.C=(NOLIST,OBJECT),
//           COND.L=(8,LT,stepname.C)
```

For this run of procedure ASMACLG, no assembler listing is produced, and running of the binder job step *//L* would be suppressed if the return code issued by the assembler (step C) were greater than 8.

When you override the PARM field in a procedure, the whole PARM field is overridden. Thus, in this example, overriding the LIST parameter effectively deletes PARM=(OBJECT,NODECK). PARM=(OBJECT,NODECK) must be repeated in the override statement; otherwise, the assembler default values are used.

3. The following example shows how to use the procedure ASMACL (Figure 44 on page 186) to:

## Using cataloged procedures

- 1** Read input from a nonlabeled 9-track tape in unit 282 that has a standard blocking factor of 10.
- 2** Put the output listing on a tape labeled TAPE10, with a data set name of PROG1 and a blocking factor of 5.
- 3** Block the SYSLIN output of the assembler and use it as input to the binder with a blocking factor of 10.
- 4** Link the module only if there are no errors in the assembly (COND=0).
- 5** Link onto a previously allocated and cataloged data set USER.LIBRARY with a member name of PROG.

```
//jobname      JOB
//stepname     EXEC  PROC=ASMACL,
//              COND.L=(0,NE,stepname.C)
//C.SYSPRINT   DD    DSN=PROG1,UNIT=TAPE,
//              VOLUME=SER=TAPE10,DCB=(BLKSIZE=665)
//C.SYSLIN     DD    DCB=(BLKSIZE=800)
//C.SYSIN      DD    UNIT=282,LABEL=(,NL),
//              DCB=(RECFM=FBS,BLKSIZE=800)
//L.SYSLIN     DD    DCB=stepname.C.SYSLIN
//L.SYSLMOD    DD    DSN=USER.LIBRARY(PROG),DISP=OLD
/*
```

The order of appearance of overriding ddnames for job step C corresponds to the order of ddnames in the procedure; that is, SYSPRINT precedes SYSLIN within step C. The ddname C.SYSIN was placed last because SYSIN does not occur at all within step C. These points are covered in the applicable *JCL Reference*.

4. The following example shows assembly of two programs, link of the two object modules produced by the assemblies into one program module, and running the generated program. The input stream appears as follows:

```
//stepname1     EXEC  PROC=ASMAC,PARM=OBJECT
//SYSIN         DD    *
:
: assembler source statements for program 1
:
/*
//stepname2     EXEC  PROC=ASMACLG
//C.SYSIN       DD    *
:
: assembler source statements for program 2
:
/*
//L.SYSIN       DD    *
: ENTRY PROG
/*
//G.ddname      DD    dd statements for G step
```

The applicable *JCL Reference* provides additional descriptions of overriding techniques.

---

## Operating system programming conventions

Assembler programs executing on z/OS must follow a set of programming conventions to save and restore registers, and access execution parameters. These conventions are described in the following sections.

## Saving and restoring general register contents

A program should save the values contained in the general registers when it receives control and, on completion, restore these same values to the general registers. Thus, as control is passed from the operating system to a program and, in turn, to a subprogram, the status of the registers used by each program is preserved. This is done through use of the SAVE and RETURN system macro instructions.

**Saving Register Contents:** The SAVE macro instruction should be the first statement in the program. It stores the contents of registers 14, 15, and 0 through 12 in an area provided by the program that passes control. When a program is given control, register 13 contains the address of an area in which the general register contents should be saved.

If the program calls any subprograms, or uses any operating system services other than GETMAIN, FREEMAIN, ATTACH, and XCTL, it must first save the contents of register 13 and then load the address of an 18-fullword save area into register 13.

**Restoring Register Contents:** At completion, the program restores the contents of general registers 14, 15, and 0 through 12 by use of the RETURN system macro instruction (which also indicates program completion). The contents of register 13 must be restored before issuing the RETURN macro instruction.

**Example:** The coding sequence that follows shows the basic process of saving and restoring the contents of the registers. A complete discussion of the SAVE and RETURN macro instructions and the saving and restoring of registers is contained in the *z/OS MVS Programming: Assembler Services Guide*.

Name	Operation	Operand
BEGIN	SAVE USING	(14,12) BEGIN,15
:		
:	ST LA	13,SAVEBLK+4 13,SAVEBLK
:		
program function source statements		
:		
:	L RETURN	13,SAVEBLK+4 (14,12)
SAVEBLK	DC	18F'0'
:		
	END	

---

## Ending program execution

You indicate completion of an assembler language source program by using the RETURN system macro instruction to pass control from the terminating program to the program that initiated it. The initiating program might be the operating system or, if a subprogram issued the RETURN, the program that called the subprogram.

## Ending program execution

In addition to indicating program completion and restoring register contents, the RETURN macro instruction can also pass a return code—a condition indicator that can be used by the program receiving control.

If the program returns to the operating system, the return code can be compared against the condition stated in the COND= parameter of the JOB or EXEC statement.

If the program returns to another program, the return code is available in general register 15 and can be used as required. Your program should restore register 13 before issuing the RETURN macro instruction.


The RETURN system macro instruction is discussed in detail in the *z/OS MVS Programming: Assembler Services Reference IAR-XCT*.

---

## Accessing execution parameters

You access information in the PARM field of an EXEC statement by referring to the contents of general register 1. When control is given to the program, general register 1 contains the address of a fullword which, in turn, contains the address of the data area containing the information.

The data area consists of a halfword containing the count (in binary) of the number of information characters, followed by the information field. The information field is aligned to a fullword boundary. Figure 47 shows how the PARM field information is structured.



---

Figure 47. Access to PARM field

---

## Object program linkage

You can combine two or more object modules, whether generated by the assembler or by another language processor, to produce a single load module. The object modules can be combined by the linkage editor, or z/OS binder, provided each object module conforms to the data formats and the required linkage conventions. This makes it possible for you to use different programming languages for different parts of your program, allowing each part to be written in the language best suited for it. Use the CALL system macro instruction to link an assembler language main program to subprograms produced by another language processor. Refer to the *z/OS MVS Programming: Assembler Services Reference* for details about linkage conventions and the CALL system macro instruction.

Figure 48 is an example of statements used to establish the assembler language program linkage to subprograms. See the applicable language programmer's guide for information about calling the language from an assembler language program.

If any input or output operations are performed by called subprograms supply the correct DD statements for the data sets used by the subprograms. See the applicable language programmer's guide for an explanation of the DD statements and special data set record formats used for the language.

---

```

ENTRPT  SAVE      (14,12)
        LR        12,15
        USING     ENTRPT,12
        ST        13,SVAREA+4
        LA        15,SVAREA
        ST        15,8(,13)
        LR        13,15

:
:
        CALL      subprogram-name,(V1,V2,V3),VL
:
:
        L         13,SVAREA+4
        RETURN    (14,12)
SVAREA  DC        18F'0'
V1      DC        CL5'Data1'
V2      DC        CL5'Data2'
V3      DC        CL5'Data3'
        END

```

---

Figure 48. Sample assembler linkage statements for calling subprograms

## Modifying program modules

If the editing functions of the binder are used to modify a program module, the entry point to the program module must be restated when the program module is reprocessed by the binder. Otherwise, the first byte of the first control section processed by the binder becomes the entry point. To enable restatement of the original entry point, or designation of a new entry point, the entry point must have been identified originally as an external symbol; that is, it must have appeared as an entry in the external symbol dictionary. The assembler automatically identifies external symbols if the entry point is the name of a control section or START statement; otherwise, you must use an assembler ENTRY statement to identify the entry point as an external symbol.

When a new object module is added to or replaces part of the load module, the entry point is restated in one of these ways:

- By placing the entry point symbol in the operand field of an EXTRN statement and an END statement in the new object module,
- By using an END statement in the new object module to designate a new entry point in the new object module,
- By using a binder ENTRY statement to designate either the original entry point or a new entry point for the program module.

Further discussion of program module entry points is contained in the *z/OS MVS Program Management: User's Guide and Reference*.





---

## Part 3. Developing assembler programs on CMS

### Chapter 10. Assembling your program on CMS 199

Input to the assembler . . . . .	199
Output from the assembler . . . . .	199
Accessing the assembler . . . . .	199
Invoking the assembler on CMS . . . . .	200
Batch assembling . . . . .	201
Controlling your assembly . . . . .	201
Input and output files . . . . .	202
Specifying the source file: SYSIN . . . . .	204
Specifying the option file: ASMAOPT . . . . .	206
Specifying macro and copy code libraries:	
SYSLIB . . . . .	206
Specifying the listing file: SYSPRINT . . . . .	206
Directing assembler messages to your terminal:	
SYSTEM . . . . .	206
Specifying object code files: SYSLIN and	
SYSPUNCH . . . . .	207
Specifying the associated data file: SYSADATA . . . . .	207
Return codes . . . . .	207
Diagnostic messages written by CMS . . . . .	207

### Chapter 11. Running your program on CMS . . 209

Using the CMS LOAD and START commands . . . . .	209
Using the CMS GENMOD command . . . . .	209
Using the CMS LKED and OSRUN commands . . . . .	210
Using the CMS batch facility . . . . .	210

### Chapter 12. CMS system services and programming considerations . . . . . 213

Using macros . . . . .	213
Assembler macros supported by CMS . . . . .	213
Adding definitions to a macro library . . . . .	213
Operating system programming conventions . . . . .	213
Saving and restoring general register contents . . . . .	213
Ending program execution . . . . .	214
Passing parameters to your assembler language program . . . . .	215



---

## Chapter 10. Assembling your program on CMS

This chapter describes how to invoke the assembler on CMS (Conversational Monitor System). It describes:

- The input to the assembler.
- The output from the assembler
- How to gain access to the High Level Assembler product files.
- How to invoke the assembler on CMS.
- How to assemble multiple source programs using the BATCH option.
- Special options for invoking the assembler on CMS.
- The data sets used by the assembler.
- The assembler return codes.
- Special diagnostic messages when invoking the assembler on CMS.

To use this section effectively, you should be familiar with the assembler language described in the *HLASM Language Reference*.

The assembler language program can be run under control of CMS. For more information about CMS, refer to the applicable *CP Command Reference for General Users* and *CMS Command and Macro Reference*.

---

### Input to the assembler

As input, the assembler accepts a program written in the assembler language as defined in the *HLASM Language Reference*. This program is referred to as a source module. Some statements in the source module (macro or COPY instructions) can cause additional input to be obtained from a macro library.

Input can also be obtained from user exits. See Chapter 4, “Providing user exits,” on page 87 for more information.

---

### Output from the assembler

The output from the assembler can consist of an object module, a program listing, terminal messages and an associated data file. The object module is stored on your virtual disk in a TEXT file. You can bring it into your virtual storage and run it by using the CMS LOAD and START commands. The program listing lists all the statements in the module, both in source and machine language format, and gives other important information about the assembly, such as error messages. The listing is described in detail in Chapter 2, “Using the assembler listing,” on page 7.

---

### Accessing the assembler

To access the High Level Assembler on CMS, you must first link to the mini-disk containing the assembler by issuing the CP LINK command. You must then issue the ACCESS command to assign a file mode, and make the mini-disk available to CMS. For example:

```
CP LINK PRODUCT 194 198 RR PASSWORD  
ACCESS 198 B
```

In this example, you have linked to disk 194 of the virtual machine that contains the High Level Assembler product, and whose user ID is PRODUCT. You have

## Accessing the assembler

defined disk 194 as 198 to your VM session. You have read access to the disk (RR) and you specified the read-share password for the 194 disk (PASSWORD).

After you linked to the 194 disk as 198, you accessed the 198 disk as disk B on your system. After you have access to the product disk, you can invoke the assembler using the ASMAHL command (see “Invoking the assembler on CMS”).


If High Level Assembler is stored on your A-disk, or another disk to which you already have access, you can omit the CP LINK and ACCESS commands. If High Level Assembler is not on a disk that you have accessed, you can put the CP LINK and ACCESS commands into your PROFILE EXEC, which issues them for you each time you log on. For more information on the CP LINK and ACCESS commands, see the applicable *CP Command Reference* for your VM environment, as listed under “Bibliography” on page 451.

---

## Invoking the assembler on CMS

Use the ASMAHL command to invoke and control assembly of assembler source programs on CMS.

The format of the ASMAHL command is:



where:

*filename*

Is the name of your assembler source program.

Use one of the three methods available for specifying your assembler source program. See “Specifying the source file: SYSIN” on page 204 for details on each of these methods.

*option* Represents one or more assembler options, separated by a space or comma, that you want in effect during assembly. These assembler options are equivalent to the options you would specify on the PARM parameter of an EXEC job control statement, if you were invoking the assembler on z/OS.

A complete list and discussion of assembler options can be found under Chapter 3, “Controlling your assembly with options,” on page 39.

The assembler options in effect are determined by the default options that were set when High Level Assembler was installed, and by the options you specify with the ASMAHL command. There are also several assembler options that can only be specified when running on CMS; see “Controlling your assembly” on page 201.

*Synonym for ASMAHL Command:* Your installation might have created a synonym for ASMAHL when High Level Assembler was installed. See your system programmer for the specific command name.

## Batch assembling

You can assemble a sequence of separate assembler programs with a single invocation of the assembler, using the BATCH option. The object programs produced from this assembly can be link-edited into either a single load module or separate load modules.

When the BATCH option is specified, each assembler program in the sequence must be terminated by an END statement, including the last program in the batch. If an END statement is omitted, the program assembles with the next program in the sequence. If the END statement is omitted from the last program in the sequence, the assembler generates an END statement.

If separate executable modules are to be produced, you must either separate the object modules, or write a NAME linkage editor control statement for each load module. The NAME statement must be written at the end of the object module. Figure 49 shows how to create two load modules, SECT1 and SECT2.

---

```

SECT1  CSECT           Start of first load module
:
      Source instructions
:
      END              End of first load module
      PUNCH ' NAME SECT1(R) '
      END
SECT2  CSECT           Start of second load module
:
      Source instructions
:
      END              End of second load module
      PUNCH ' NAME SECT2(R) '
      END

```

---

Figure 49. Example of creating two load modules on CMS

If separate TEXT files are required, you must either manually separate the BATCH-produced object modules into separate TEXT files, or issue two separate ASMAHL commands for separate source modules.

## Controlling your assembly

The assembly options are specified on the ASMAHL command after the left parenthesis. The options that can be specified to control your assembly are described in Chapter 3, “Controlling your assembly with options,” on page 39.

On CMS, there are additional options that can be specified. These are described in Chapter 3, “Controlling your assembly with options,” on page 39, and consist of:

**ERASE**                Deletes LISTING, TEXT, and SYSADATA files before the assembly begins.


## Controlling your assembly

<b>LINECOUNT</b>	Specifies the number of lines to be printed on each page of the assembler listing.
<b>NOSEG</b>	Specifies that the assembler load modules are loaded from disk. The default is to load the modules from the Logical Saved Segment (LSEG); but, if the LSEG is not available, then load the modules from disk.
<b>PRINT</b>	Directs the assembler listing to the virtual printer, instead of to disk.
<b>SEG</b>	Specifies that the assembler load modules are loaded from the Logical Saved Segment (LSEG). The default is to load the modules from the LSEG; but, if the LSEG is not available, then load the modules from disk.
<b>SYS Parm</b>	A question mark (?) can be specified in the SYS Parm string, which instructs the assembler to prompt you for a character string at your terminal.

---

## Input and output files

Depending on the options in effect, High Level Assembler requires the files as shown in Figure 50.



---

Figure 50. High Level Assembler Files

The ddnames can be overridden during installation.

High Level Assembler requires the following files:

<b>SYSIN</b>	An input file containing the source statements to be processed.
<b>SYSLIB</b>	A file containing macro definitions (for macro definitions not defined in the source program), source code to be called for through COPY assembler instructions, or both.
<b>SYS PRINT</b>	A file containing the assembly listing (if the LIST option is in effect).
<b>SYSTEM</b>	A file containing essentially a condensed form of SYS PRINT, principally error flagged statements and their error messages (only if the TERM option is in effect).

- SYSPUNCH** A file containing object module output, usually for punching (only if the DECK option is in effect).
- SYSLIN** A file containing object module output usually for the linkage editor (only if the OBJECT option is in effect).
- SYSADATA** A file containing associated data output (only if the ADATA option is in effect).

The files listed above are described in the text following Table 29. The characteristics of these files, those set by the assembler and those you can override, are shown in Table 29.

*Table 29. Assembler file characteristics*

File	Access Method	Logical Record Length (LRECL)	Block Size (BLKSIZE)	Record Format (RECFM)
SYSIN	QSAM	80	<b>4</b>	<b>7 10</b>
ASMAOPT	QSAM	<b>11</b>	<b>6</b>	Fixed/Variable
SYSLIB	BPAM	80	<b>5</b>	<b>7 10</b>
SYSPRINT	QSAM	<b>1</b>	<b>6</b>	<b>8 10</b>
SYSTEM	QSAM	<b>2</b>	<b>4</b>	<b>9 10</b>
SYSPUNCH	QSAM	<b>12</b>	<b>4</b>	<b>3</b>
SYSLIN	QSAM	<b>12</b>	<b>4</b>	<b>3</b>
SYSADATA	QSAM	32756	32760 or greater	VB

**Notes to Table 29:**

- 1** If you specify EXIT(PRTEXT) and the user exit specifies the logical record length, the logical record length returned is used, unless the SYSPRINT data set has a variable-length record format in which case the LRECL used is 4 bytes greater than the value returned by the exit. If EXIT(PRTEXT) has not been specified or the user exit does not specify a record length, the record length from the FILEDEF command or file label is used, if present. Otherwise, the record length defaults to 133, or 137 if the record format is variable-length.

The minimum record length allowed for SYSPRINT is 121, and the maximum allowed is 255. If the record format is variable-length, the LRECL should be at least 125 or 137 depending on the LIST option.

- 2** If you specify EXIT(TRMEXIT) and the user exit specifies the logical record length, the logical record length returned is used. If you do not specify EXIT(TRMEXIT) or the user exit does not specify a record length, the record length from the FILEDEF command or file label is used, if present. If not present, the record length defaults to the record length for SYSPRINT (if the LIST option is in effect) or 133 otherwise.

The maximum record length allowed for SYSTEM is 255.

- 3** Both fixed and variable formats are supported; the default is fixed.

- 4** If specified, the BLKSIZE must equal the LRECL, or be a multiple of the LRECL. If BLKSIZE is not specified, it is set to LRECL.

- 5** The BLKSIZE on the FILEDEF command or the file label must equal the LRECL, or be a multiple of the LRECL.

- 6** The blocksize must be equal to or a multiple of the record length if the record format is fixed. If the record format is variable, then the blocksize must be at least 4 bytes greater than the record length.
- 7** Set by the assembler to F (or FB) if necessary.
- 8** Both fixed and variable formats are supported; the default is variable. If the FILEDEF command or file label specifies machine or ASA control characters, the ASA option is set or reset accordingly. If machine or ASA control characters are not specified on the FILEDEF command or file label, the record format is modified according to the ASA option.
- 9** Set by the assembler to F (or FB) if necessary. The record format is set to FA (or FBA) if the ASA option is specified, or FM (or FBM) otherwise.
- 10** You can specify B, S, or T, or any combination of these.
- 11** The minimum record length allowed for ASMAOPT is 5. The maximum record length allowed is 32756 if the record format is variable-length or 32760 if the record format is fixed-length.
- 12** If you specify the OBJECT option, the logical record length must be 80. If you specify the GOFF option, the object module can be generated with either fixed-length records of 80 bytes, or variable-length records up to a BLKSIZE of 32720.

### Specifying the source file: SYSIN

Use one of these methods for specifying your assembler source program:

- Specify the filename of the assembler source program on the ASMAHL command line,
- Issue a FILEDEF for SYSIN before issuing the ASMAHL command,
- Supply source statements from a user-supplied module by using the EXIT assembler option.

*Specify the Filename on the Command Line:* Using this method, you specify the filename of your assembler source program on the ASMAHL command line. For example:

```
ASMAHL PROG1 (LIST,XREF(SHORT))
```

assembles the source program named PROG1 using the assembler options LIST and XREF(SHORT). The source program must have a filetype of ASSEMBLE. The ASMAHL command issues the following FILEDEF command:

```
FILEDEF SYSIN DISK PROG1 ASSEMBLE * (RECFM FB LRECL 80 BLOCK 16000)
```

*Issue a FILEDEF for SYSIN:* Another method you can use to specify the assembler source program is to issue a FILEDEF for SYSIN before the assembly. The assembler then assembles the program specified in the FILEDEF. For example:

```
FILEDEF SYSIN DISK PROG2 ASSEMBLE A  
ASMAHL (LIST,XREF)
```

assembles the program named PROG2, using the options specified on the ASMAHL command line. When you issue a FILEDEF for SYSIN, the source program you specify with the FILEDEF is the one used for input by the assembler.

If the FILEDEF for SYSIN is issued and the FILEDEF specifies a DISK file, the filename on the ASMAHL command is optional. If the filename is specified on the



ASMAHL command, the filename must match the filename of the file specified on the FILEDEF. Additionally, when using a FILEDEF, the file type need not be ASSEMBLE.

You can read z/OS data sets and z/VSE files as CMS files by defining those data with the FILEDEF command. For example,

```
FILEDEF SYSIN DISK OSDS ASSEMBLE fm DSN OS DATASET (options...
```

You can also assemble a member of an OS partitioned data set or a CMS MACLIB by using the MEMBER parameter of the FILEDEF command. When you specify member parameter, the member name is used as the filename for the LISTING, TEXT, and SYSADATA files.

If you want to assemble a source file that is in your CMS virtual reader, issue the following FILEDEF command:

```
FILEDEF SYSIN READER
```

and then issue the ASMAHL command. You must specify the filename on the ASMAHL command. The filename is used as the file name of the LISTING, TEXT, and SYSADATA files.

Similarly, if you have a tape containing an assembler input file that you want to assemble, you must issue the following command before issuing the ASMAHL command:

```
FILEDEF SYSIN TAPn (RECFM F LRECL 80 BLOCK 80
```

If the blocksize of the file were 800 bytes, you could specify BLOCK 800 as in the preceding FILEDEF.

If the FILEDEF command specifies a tape file, the filename must be specified on the ASMAHL command. The filename is used as the filename of the LISTING, TEXT, and SYSADATA files.

Make sure that any attributes specified for a file conform to the attributes expected by the assembler for the device.

**Specify Source Using the EXIT Option:** If you are using an input user exit to provide source statements to the assembler, the FILEDEF for SYSIN is not required. For example:

```
ASMAHL PROG2 (EXIT(INEXIT(INMOD1('ABCD'))),LIST,XREF(SHORT))
```

assembles the source statements provided by the input user module named INMOD1 using the character string ABCD, and also the assembler options LIST and XREF(SHORT). (For specific details on using the EXIT assembler option, see page 51).

Specify the filename on the ASMAHL command, or a FILEDEF for SYSIN, before issuing the ASMAHL command as described above. This is required even if the assembler does not read the input file. The filename specified on the ASMAHL command, or from the FILEDEF for SYSIN, is used as the filename of the LISTING, TEXT, and SYSADATA files.

If you specify the INEXIT option, the ASMAHL command does not check whether the input file exists. If the SOURCE user exit instructs the assembler to open the primary input file, the open fails if the file does not exist.

### Specifying the option file: ASMAOPT

You must issue an ASMAOPT FILEDEF command if you wish the assembler to use the options in this file. For example

```
FILEDEF ASMAOPT DISK PROG1 OPTIONS *
```

### Specifying macro and copy code libraries: SYSLIB

If you don't issue SYSLIB FILEDEF before the ASMAHL command, the ASMAHL command issues the following FILEDEF command:

```
FILEDEF SYSLIB DISK CMSLIB MACLIB * (RECFM FB LRECL 80 BLOCK 8000
```

Use the GLOBAL command to identify which CMS libraries are to be searched for macro definitions and COPY code. Private libraries and CMSLIB can be concatenated with each other in any order by the GLOBAL command. The format of this command is described in the applicable *CMS Command and Macro Reference*.

You can concatenate a CMS MACLIB with an OS partitioned data set. When this is required, the library with the largest blocksize must be specified first, as in the following example:

```
FILEDEF SYSLIB DISK MYLIB MACLIB M DSN ATR005.MACLIB  
FILEDEF SYSLIB DISK OSMACRO MACLIB S (CONCAT  
GLOBAL MACLIB MYLIB OSMACRO
```

### Specifying the listing file: SYSPRINT

If you specify the PRINT option, and you don't issue SYSPRINT FILEDEF before the ASMAHL command, the ASMAHL command issues the following FILEDEF command:

```
FILEDEF SYSPRINT PRINTER
```

If you specify the DISK option (which is the default), and you don't issue SYSPRINT FILEDEF before the ASMAHL command, the ASMAHL command issues the following FILEDEF command:

```
FILEDEF SYSPRINT DISK fn LISTING m1 (RECFM VB BLOCK 13300
```

where *fn* is the filename specified on the ASMAHL command. If the assembler source file (SYSIN input) is not on disk or is on a read-only disk, the file mode *m* is set to the first available read/write disk. If the source file is on a read/write disk, the mode letter *m* is set to the mode of that read/write disk. For example, if the source file were on a read/write B disk, the file mode *m1* would be set to "B1".

You can issue a FILEDEF command for SYSPRINT before the ASMAHL command to direct the listing to the terminal, printer, or a disk file. See "PRINT (CMS)" on page 69 for details about the CMS options for SYSPRINT.

### Directing assembler messages to your terminal: SYSTEM

If you don't issue a SYSTEM FILEDEF command before the ASMAHL command, the ASMAHL command issues the following FILEDEF command:

```
FILEDEF SYSTEM TERMINAL
```

You can issue a FILEDEF command for SYSTEM before the ASMAHL command to direct the listing to the terminal, printer, or a disk file.

## Specifying object code files: SYSLIN and SYSPUNCH

If you don't issue a SYSPUNCH or SYSLIN FILEDEF command before the ASMAHL command, the ASMAHL command issues the following FILEDEF commands:

```
FILEDEF SYSPUNCH PUNCH
FILEDEF SYSLIN DISK fn TEXT m1 (RECFM FB LRECL 80 BLOCK 16000
```

where *fn* is the filename specified on the ASMAHL command. If the assembler source file (SYSIN input) is not on disk or is on a read-only disk, the file mode *m* is set to the first available read/write disk. If the source file is on a read/write disk, the mode letter *m* is set to the mode of that read/write disk. For example, if the source file were on a read/write B disk, the file mode *m1* would be set to "B1".

You can issue a FILEDEF command for SYSPUNCH or SYSLIN before the ASMAHL command is issued to direct the object output to the punch or a disk file.

## Specifying the associated data file: SYSADATA

If you don't issue a SYSADATA FILEDEF command before the ASMAHL command, the ASMAHL command issues the following FILEDEF command:

```
FILEDEF SYSADATA DISK fn SYSADATA m1 (RECFM VB LRECL 32756 BLOCK 32760
```

where *fn* is the filename specified on the ASMAHL command, and if the assembler source file (SYSIN input) is *not* on disk or is on a read-only disk, the file mode *m* is set to the first available read/write disk. If the source file is on a read/write disk, the mode letter *m* is set to the mode of that read/write disk. For example, if the source file were on a read/write B disk, the file mode *m1* would be set to "B1".

A FILEDEF command for SYSADATA can be issued before the ASMAHL command is issued to direct the associated data output to a different file.

---

## Return codes

High Level Assembler issues return codes that are returned to the caller. If High Level Assembler is called from an EXEC, the EXEC can check the return code.

The return code issued by the assembler is the highest severity code that is associated with any error detected in the assembly, or with any MNOTE message produced by the source program or macro instructions. The return code can be controlled by the FLAG(*n*) assembler option described on page 54. See Appendix G, "High Level Assembler messages," on page 335 for a listing of the assembler errors and their severity codes.

---

## Diagnostic messages written by CMS

If an error occurs during the running of the ASMAHL command, a message might be written at the terminal and, at completion of the command, register 15 contains a non-zero return code.

Two types of messages might be issued:

- Messages that are issued by the assembler (see Appendix G, "High Level Assembler messages," on page 335).
- Messages that are issued by the ASMAHL command processor (see "ASMAHL Command Error Messages (CMS)" on page 385).

## Diagnostic messages written by CMS

The messages issued by the ASMAHL command processor are in two parts: a message code and the message text. The message code is in the form `ASMACMSnnnt`, where `ASMACMS` indicates that the message was generated by the ASMAHL command program, `nnn` is the number of the message, and `t` is the type of message. The message text describes the error condition.

You can use the CP command `SET EMSG` to control what part of the diagnostic message to display. Table 30 shows the `SET EMSG` options you can specify, and how they affect the message display.

*Table 30. CP SET EMSG command options*

SET EMSG Option	Part of Message Displayed
CODE	Displays the message code only.
OFF	Suppresses the entire message text and message code.
ON	Displays the entire message text and the message code.
TEXT	Displays the message text only.

Refer to the applicable *CP Command Reference for General Users* for details about the CP `SET` command.

When you specify the `TERM` assembler option, diagnostic messages are written to the terminal in the form `ASMAnnns`. Errors detected by the ASMAHL command program, which terminate the command before High Level Assembler is called, result in error messages (type E).

---

## Chapter 11. Running your program on CMS

There are three ways to run your assembled program under any level of CMS:

- Using the CMS LOAD and START commands.
- Using the CMS GENMOD command to create a program module and then using the module filename to cause the module to be run.
- Using the CMS LKED and OSRUN commands.

Any of these three methods can be used under the control of the CMS batch facility.

---

### Using the CMS LOAD and START commands

After you have assembled your program, you can run the object program in the TEXT file produced by the assembler. The TEXT file produced is relocatable and can be run merely by loading it into virtual storage with the LOAD command and using the START command to begin running. For example, if you have assembled a source program named CREATE, you have a file named CREATE TEXT. Use the LOAD command to load your program into storage, and then use the START command to run the program:

```
LOAD CREATE
START
```

In this example, the file CREATE TEXT contains the object code from the assembly.

The CMS START command can be used to pass user-defined parameters. For a complete description of the START command, see the applicable *CMS Command Reference* for your VM environment, as listed under “Bibliography” on page 451.

---

### Using the CMS GENMOD command

When your programs are debugged and tested, you can use the LOAD and INCLUDE commands, in conjunction with the GENMOD command, to create program modules. A module is a relocatable or non-relocatable object program whose external references have been resolved. In CMS, these files must have a filetype of MODULE.

To create a program module, load the TEXT files or TXTLIB members into storage and issue the GENMOD command:

```
LOAD CREATE ANALYZE PRINT(RLDSAVE
GENMOD PROCESS
```

In this example, CREATE, ANALYZE, and PRINT are TEXT files that you are combining into a module named PROCESS; PROCESS is the filename you are assigning to the module, which has a filetype of MODULE. If you use the name of an existing MODULE file, the old one is replaced.

From then on, any time you want to run the program composed of the object files CREATE, ANALYZE, and PRINT, enter:

```
PROCESS
```

## Using the CMS GENMOD command

If PROCESS requires input files, output files, or both, you must define these files before PROCESS can run correctly.

For more information on creating program modules, see the applicable *CMS User's Guide* for your particular VM environment, as listed under "Bibliography" on page 451.

---

## Using the CMS LKED and OSRUN commands

A LOADLIB is another type of library available to you on CMS. LOADLIBs, like MACLIBs and TXTLIBs, are in CMS-simulated partitioned data set formats. Unlike TXTLIBs, which contain object programs that need to be link-edited when they are loaded, LOADLIBs contain programs that have already been link-edited, thus saving the overhead of the link-editing process every time the program is loaded. You can load the members of TXTLIBs by both CMS loading facilities (LOAD or INCLUDE command) and certain OS macros (such as LINK, LOAD, ATTACH, or XCTL), but you can only load the members of LOADLIBs that use these OS macros.

Use the LKED command to create a CMS LOADLIB. For example:

```
FILEDEF SYSLIB DISK USERTXT TXTLIB *  
LKED TESTFILE
```

This example takes a CMS TEXT file with the filename of TESTFILE and creates a file named TESTFILE LOADLIB, using the SYSLIB to resolve external references. TESTFILE LOADLIB is a CMS-simulated partitioned data set containing one member, named TESTFILE.

To use the OSRUN command to run TESTFILE, first use the GLOBAL command to identify which libraries are to be searched when processing subsequent CMS commands. For example:

```
GLOBAL LOADLIB TESTFILE  
OSRUN TESTFILE
```

The OSRUN command causes the TESTFILE member of the TESTFILE LOADLIB to be loaded, relocated, and run.

User parameters can be added on the line with the OSRUN command, but they are passed in OS format. For a complete description of the OSRUN command, see the applicable *CMS Command Reference* for your particular VM environment, as listed under "Bibliography" on page 451.

---

## Using the CMS batch facility

The CMS batch facility provides a way of submitting jobs for batch processing in CMS, and can be used to run an assembler program. You can use this facility in one of these situations:

- You have a job that takes a lot of time, and you want to be able to use your terminal for other work while the job is running,
- You do not have access to a terminal.

The CMS batch facility is really a virtual machine, generated and controlled by the system operator, who logs onto VM using the batch user ID and invokes the CMSBATCH command. All jobs submitted for batch processing are spooled to the

user ID of this virtual machine, which runs the jobs sequentially. To use the CMS batch facility at your location, you must contact the system operator to learn the user ID of the batch virtual machine.

You can run High Level Assembler under the control of the CMS batch facility. Terminal input can be read from the console stack. In order to prevent your batch job from being cancelled, make sure that stacked input is available if your program requests input from the terminal. For further information on using the CMS batch facility, see the applicable *CMS User's Guide* for your particular VM environment, as listed under "Bibliography" on page 451.





---

## Chapter 12. CMS system services and programming considerations

This chapter describes some of the CMS system services and program development facilities that assist you in developing your assembler program. It provides the following information:

- Assembler macros supported by CMS.
- Adding definitions to a macro library.
- Saving and restoring general register contents.
- Ending program execution.
- Passing parameters to your assembler language program.

---

### Using macros

This section tells you about the assembler macros supported by CMS, and tells you how to add definitions to a macro library.

#### Assembler macros supported by CMS

There are several CMS assembler macros you can use in assembler programs. Among the services provided by these macros are: the ability to write a record to disk, to read a record from disk, to write lines to a virtual printer, and so on. All the CMS assembler macros are described in the applicable *CMS Command and Macro Reference*, listed under “Bibliography” on page 451.

#### Adding definitions to a macro library

Macro definitions, and members containing assembler source statements that can be read by a COPY instruction, can be added to a macro library. Use the CMS MACLIB command to create and modify CMS macro libraries. In the following example, a macro with a filename of NEWMAC and filetype of MACRO is added to the MACLIB with a filename of MYLIB.

```
MACLIB ADD MYLIB NEWMAC
```

Details of this command are described in the applicable *CMS Command and Macro Reference*, listed under “Bibliography” on page 451.

---

### Operating system programming conventions

Assembler programs executing on CMS must follow a set of programming conventions to save and restore registers, and access execution parameters. These conventions are described in the following sections.

#### Saving and restoring general register contents

A program should save the values contained in the general registers when it receives control and, on completion, restore these same values to the general registers. Thus, as control is passed from the operating system to a program and, in turn, to a subprogram, the status of the registers used by each program is preserved. This is done through use of the SAVE and RETURN system macro instructions.

***Saving Register Contents:*** The SAVE macro instruction should be the first statement in the program. It stores the contents of registers 14, 15, and 0 through

## Operating system programming conventions

12 in an area provided by the program that passes control. When a program is given control, register 13 contains the address of an area in which the general register contents should be saved.

If the program calls any subprograms, or uses any operating system services other than GETMAIN, FREEMAIN, ATTACH, and XCTL, it must first save the contents of register 13 and then load the address of an 18-fullword save area into register 13. This save area is in the program and is used by any subprograms or operating system services called by the program.

**Restoring Register Contents:** At completion, the program restores the contents of general registers 14, 15, and 0 through 12 by use of the RETURN system macro instruction (which also indicates program completion). The contents of register 13 must be restored before issuing the RETURN macro instruction.

**Example:** The coding sequence that follows shows the basic process of saving and restoring the contents of the registers. See the *VM/ESA CMS Application Development Reference for Assembler* for further information about the SAVE and RETURN macros.

Name	Operation	Operand
CSECTNAM	SAVE	(14,12)
	USING	CSECTNAM,15
:		
	ST	13,SAVEAREA+4
	LA	13,SAVEAREA
:		
:		
program function source statements		
:		
	L	13,SAVEAREA+4
	RETURN	(14,12)
SAVEAREA	DC	18F'0'
:		
	END	

---

## Ending program execution

You indicate completion of an assembler language source program by using the RETURN system macro instruction to pass control from the terminating program to the program that initiated it. The initiating program may be the operating system or, if a subprogram issued the RETURN, the program that called the subprogram.

In addition to indicating program completion and restoring register contents, the RETURN macro instruction may also pass a return code—a condition indicator that may be used by the program receiving control.

If the program returns to the operating system, the return code can be compared against the condition stated in the COND= parameter of the JOB or EXEC statement.

If return is to another program, the return code is available in general register 15, and may be used as required. Your program should restore register 13 before issuing the RETURN macro instruction.

The RETURN system macro instruction is discussed in detail in the *VM/ESA CMS Application Development Reference for Assembler*.

## Passing parameters to your assembler language program

On CMS, you can pass parameters to an assembler language program by means of the START command. The statement below shows how to pass parameters to your program using the CMS START command:

```
START MYJOB PARM1 PARM2
```

The parameters must be no longer than 8 characters each, and must be separated by spaces.

CMS creates a list of the parameters that are passed to the program when it is run. The address of the parameters is passed in register 1. The parameter list for the command above is:

```
PLIST    DS    0D
          DC    CL8'MYJOB'
          DC    CL8'PARM1'
          DC    CL8'PARM2'
          DC    8X'FF'
```

where the list is terminated by hexadecimal FFs.

If your program is started using the CMS OSRUN command, the parameters are passed in the same way as described for z/OS in “Accessing execution parameters” on page 194.

If a module was created using the CMS GENMOD command and run using the MODULE name, the parameters are passed in extended parameter list format. The address of the parameter list is passed in register 0.

The format of the extended parameter list is:

Offset	Field
0	Address of command name
4	Address of beginning of options
8	Address of end of options
12	User word
16	Reserved



---

## Part 4. Developing assembler programs on z/VSE

### Chapter 13. Assembling your program on z/VSE 219

Input to the assembler . . . . .	219
Output from the assembler . . . . .	219
Invoking the assembler in batch . . . . .	219
Invoking the assembler on ICCF . . . . .	220
Invoking the assembler dynamically. . . . .	222
Batch assembling . . . . .	223
Controlling your assembly . . . . .	224
Input and output files . . . . .	225
Specifying the source file: SYSIPT . . . . .	227
Specifying macro and copy code libraries:	
LIBDEF job control statement . . . . .	227
Specifying the listing file: SYSLST . . . . .	227
Directing assembler messages to your console	
log: SYSLOG . . . . .	227
Specifying object code files: SYSLNK and	
SYSPCH . . . . .	228
Specifying the associated data file: SYSADAT	228
Return codes . . . . .	228

### Chapter 14. Link-editing and running your program on z/VSE . . . . . 229

The linkage editor. . . . .	229
Creating a phase . . . . .	229
Input to the linkage editor . . . . .	229
Inputting object modules . . . . .	230
Files for linkage editor processing . . . . .	230
Inputting additional object modules . . . . .	231
Linkage editor control statements. . . . .	231
Output from the linkage editor . . . . .	232
Running your assembled program . . . . .	232

### Chapter 15. z/VSE system services and programming considerations . . . . . 233

Adding definitions to a macro library . . . . .	233
Processing E-decks . . . . .	233
Operating system programming conventions . . . . .	234
Saving and restoring general register contents	234
Ending program execution . . . . .	234
Accessing execution parameters . . . . .	235



---

## Chapter 13. Assembling your program on z/VSE

This chapter describes how to invoke High Level Assembler on z/VSE. It describes the job control required to run the assembler, files used by the assembler and return codes. The job control language is described in detail in *VSE/ESA System Control Statements*.

---

### Input to the assembler

As input, the assembler accepts a program written in the assembler language as defined in the *HLASM Language Reference*. This program is referred to as a *source module*. Some statements in the source module (macro or COPY instructions) can cause additional input to be obtained from a macro library.

---

### Output from the assembler

The output from the assembler can consist of an object module, a program listing, terminal messages, and an associated data file. The object module can be written to a data set residing on a direct access device or a magnetic tape. From that file, the object module can be read and processed by the linkage editor or the loader. See Appendix C, “Object deck output,” on page 259 for the format of the object module.

The program listing lists all the statements in the module, both in source and machine language format, and gives other important information about the assembly, such as error messages. The listing is described in detail in Chapter 2, “Using the assembler listing,” on page 7.

---

### Invoking the assembler in batch

The JCL for running an assembly includes:

- A job description.
- Definitions for the files needed.
- A statement to run the assembler.

The following example shows how to run the assembler.

---

```
// JOB jobname
// DLBL IJSYS03,'HLASM.WORK.IJSYS03',0,VSAM,RECSIZE=4096,
//          RECORDS=(100,50),DISP=(NEW,KEEP),CAT=VSESPUC
// DLBL IJSYSLN,'HLASM.WORK.IJSYSLN',0,VSAM,RECSIZE=322,
//          RECORDS=(100,50),DISP=(NEW,KEEP),CAT=VSESPUC
// LIBDEF PHASE,SEARCH=(PRD2.PROD)
// LIBDEF SOURCE,SEARCH=(lib.sublib)
// OPTION LINK
// EXEC ASMA90,SIZE=ASMA90
:
:
Assembler source statements
:
/*
/&
```

---

Figure 51. JCL to assemble a program

## Invoking the assembler in batch

- 1** Identifies the beginning of your job to the operating system. *jobname* is the name you assign to the job.
- 2** Defines the work file to be used by the assembler. The work file must be on a direct-access storage device. The work file can be a SAM file or a SAM-ESDS file. This statement is not required if IJSYS03 is defined in the System Standard or Partition Standard labels.
- 3** Defines the SYSLNK file that receives the object records produced from the LINK option. This statement is not required if IJSYSLN is defined in the System Standard or Partition Standard labels.
- 4** Specifies the sublibrary where the assembler resides.
- 5** Specifies the sublibraries that are to be searched to locate any macro and copy members, and the ASMAOPT.USER member (if required).
- 6** Sets the LINK option and the Assembler OBJECT option which causes the assembler to write the object records produced to SYSLNK.
- 7** Invokes the assembler to process the assembler source statements that follow the EXEC statement.

The SIZE parameter of the EXEC statement specifies SIZE=ASMA90. This sets the size of program storage to the size of the phase ASMA90 and makes all the remaining storage in the partition GETVIS storage. High Level Assembler does not use program storage.
- 8** The end-of-data statement indicates the end of input to the assembler (source code), and separates data from subsequent job control statements in the input stream.
- 9** The end-of-job statement indicates the end of the job.

These statements cause the assembler to assemble your program and to produce a listing (described in Chapter 2, “Using the assembler listing,” on page 7) and an object module (described in Appendix C, “Object deck output,” on page 259).

---

## Invoking the assembler on ICCF

To assemble your program on ICCF, use the job entry statements /LOAD, /OPTION, /INCLUDE, and /RUN. To create and save an object module, you should also use the /FILE job entry statement.

Before assembling your program on ICCF, ensure that your ICCF Administrator has provided the following:

- LIBDEF statements for all librarian sublibraries that are accessed during assembly, including the sublibrary where High Level Assembler and any user exits reside. The LIBDEF statements must be provided in the VSE/ICCF CICS® initialization job stream.
- Definitions for the assembler work file used by the assembler to process the source program. All work files must be pre-allocated, and defined in the VSE/ICCF initialization job stream. High Level Assembler does not recognize work files defined using the /FILE job entry statement.
- An interactive partition with sufficient storage to run the assembly. The amount of storage you need depends upon the size of your source program, and the value you specify in the SIZE assembler option.

On ICCF, you can either enter the required ICCF commands, or you can write your own procedure that can be used whenever you need to assemble a program.



Figure 52 shows an example of the ICCF commands you should enter to assemble your program.

---

```
/INPUT  
/LOAD   ASMA90,PARM='SIZE(800K)'  
/OPTION NOGO,RESET,DECK,GETVIS=P-240  
/FILE    TYPE=ICCF,UNIT=SYSPCH,NAME=ASMOBJ  
/INCLUDE ASMPROG  
/END  
/RUN
```

---

*Figure 52. Entering ICCF commands*

Figure 53 on page 222 shows a working example of an ICCF procedure for assembling a program, and generating an object module.

## Invoking the assembler dynamically

```
* -----
*  ASMARUN NNNN (OBJ MMM/*) OPTIONS
*
*  PROCEDURE TO ASSEMBLE A HIGH LEVEL ASSEMBLER PROGRAM
*  -----
&&OPTIONS 0010011
&&IF &&PARMCT NE 0 &&GOTO START
&&TYPE ENTER NAME (OBJ NAME/*) (OPTIONS)
&&READ &&PARAMS
&&IF &&PARMCT EQ 0 &&EXIT
&&LABEL START
/LIST 1 1 &&PARAM1 &&VARBL5
&&IF &&RETCOD NE *FILE &&GOTO SOUR
&&TYPE *SOURCE MEMBER &&PARAM1 NOT IN LIBRARY OR EMPTY
&&EXIT
&&LABEL SOUR
&&IF &&RETCOD NE *INVALID &&GOTO YESOR
&&TYPE *INVALID PASSWORD OR INVALID ACCESS TO MEMBER &&PARAM1
&&EXIT
&&LABEL YESOR
&&IF &&RETCOD NE *MISSING &&GOTO OKSOR
&&TYPE *ENTER PASSWORD FOR MEMBER &&PARAM1
&&READ &&VARBL5
&&IF &&VARBL5 NE ' ' &&GOTO -START
&&EXIT
&&LABEL OKSOR
&&SET &&VARBL1 &&PARAM1
&&SHIFT 1
&&IF &&PARAM1 NE OBJ &&GOTO NOOBJ
&&SET &&VARBL2 &&PARAM2 ' '
&&IF &&VARBL2 EQ '*' &&SET &&VARBL2 ' '
&&IF &&VARBL2 EQ ' ' &&GOTO +INLIB
/LIST 1 1 &&VARBL2
&&IF &&RETCOD NE *FILE &&GOTO OVERW
/INP NOPROMPT
DUMMY RECORD TO CREATE A MEMBER FOR 'ASMARUN' PROCEDURE OUTPUT
/SAVE &&VARBL2
&&IF &&RETCOD NE *LIBRARY &&GOTO INLIB
&&TYPE *LIBRARY DIRECTORY FULL
&&EXIT
&&LABEL OVERW
&&TYPE *MEMBER &&VARBL2 ALREADY EXISTS. OVERWRITE? (Y/N)
&&READ &&VARBL4
&&IF &&VARBL4 EQ 'Y' &&GOTO INLIB
&&TYPE *NO ASSEMBLY - TRY AGAIN WITH ANOTHER NAME
&&EXIT
&&LABEL INLIB
&&SHIFT 1
&&SHIFT 1
&&LABEL NOOBJ
/INP NOPROMPT
&/LOAD ASMA90 PARM='&&PARAM1,&&PARAM2,&&PARAM3,&&PARAM4,&&PARAM5'
/OPTION NOGO RESET GETVIS=P-240
&&IF &&VARBL2 NE ' ' /FILE TYPE=ICCF,UNIT=SYSPCH,NAME=&&VARBL2
&/INCLUDE &&VARBL1 &&VARBL5
/END
/PEND
/RUN
```

Figure 53. Sample procedure for assembling on ICCF

## Invoking the assembler dynamically

To invoke High Level Assembler from a running program, use the CDLOAD and CALL macro instructions.

You can supply assembler options in the CALL macro instruction as shown in Figure 54 on page 223

---

```

DYNAMICV CSECT
DYNAMICV RMODE 24
DYNAMICV AMODE ANY
BEGIN    SAVE (14,12)
        USING BEGIN,15
        ST    13,SAVEAREA+4
        LA    13,SAVEAREA
        CDLOAD ASMA90 1
        LR    15,0
        CALL (15),(OPTIONS) 2 3
        CDDELETE ASMA90
        L     13,SAVEAREA+4
        RETURN (14,12)
SAVEAREA DS 18F
OPTIONS  DC Y(OPTIONSL)
OPTS     DC C'XREF(SHORT)'
OPTIONSL EQU *-OPTS
END

```

---

Figure 54. Sample program to call the assembler dynamically

**Notes on Figure 54:**

- 1** ASMA90 is the symbolic name of the assembler. The entry point address is returned by CDLOAD in register 0.
- 2** (15) specifies that the entry point address is in register 15.
- 3** (OPTIONS) specifies the address of a variable-length list containing the options. The address of an option list must be provided, even if no options are required.

The option list must begin on a halfword boundary. The first two bytes contain a count of the number of bytes in the remainder of the list. If no options are specified, the count must be zero. The option list is free form, with each field separated from the next by a comma. No spaces should appear in the list, except within the string specified for the EXIT or SYSPARM options providing the string is enclosed within single quotation marks.

---

## Batch assembling

You can assemble a sequence of separate assembler programs with a single invocation of the assembler by specifying the BATCH option. The object programs produced from this assembly can be link-edited into either a single phase or separate phases.

When the BATCH option is specified, each assembler program in the sequence must be terminated by an END statement, including the last program in the batch. If an END statement is omitted, the program is assembled with the next program in the sequence. If the END statement is omitted from the last program in the sequence, the assembler generates an END statement.

If you need to produce separate phases, you must write a phase linkage editor control statement for each phase. The phase statement must be written at the start of the module. The following example shows how to create two phases, SECT1 and SECT2. When multiple phases are produced, they are link-edited as an overlay.

```

        PUNCH ' PHASE SECT1,*'
        END
SECT1   CSECT           Start of first load module

```

## Batch assembling

```
⋮
      Source instructions
⋮
      END          End of first load module
      PUNCH ' PHASE SECT2,*'
      END
SECT2  CSECT      Start of second load module
⋮
      Source instructions
⋮
      END          End of second load module
```

---

## Controlling your assembly

The assembler options are specified on the PARM parameter of the JCL EXEC statement or the ICCF /LOAD job entry statement. The options must be enclosed within single quotes and be separated by commas.

The assembler options are described in Chapter 3, “Controlling your assembly with options,” on page 39. You can also specify some assembler options using the // OPTION job control statement. These are described in Table 31.

*Table 31. Assembler options in JCL*

Assembler Option	JCL OPTION Equivalent	Comments
ALIGN	ALIGN	
DECK	DECK	The DECK assembler option is always specified using the JCL OPTION statement. If the DECK option is specified on the PARM operand of the JCL EXEC statement, error diagnostic message ASMA400W is issued, and the DECK option is ignored.
LIST	LIST	The LIST assembler option is equivalent to specifying LIST(121).
OBJECT	LINK CATAL	The OBJECT assembler option is always specified using the LINK or CATAL option of the JCL OPTION statement. If the OBJECT option is specified on the PARM operand of the JCL EXEC statement, error diagnostic message ASMA400W is issued, and the OBJECT option is ignored.
RLD	RLD	

Table 31. Assembler options in JCL (continued)

Assembler Option	JCL OPTION Equivalent	Comments
SYS Parm	SYS Parm	The value specified in the SYS Parm option of the JCL OPTION statement is limited to 8 characters. To provide longer values, use the SYS Parm assembler option. The SYS Parm value specified on the Parm operand of the JCL EXEC statement overrides any value specified on the JCL OPTION statement. A null value (// OPTION SYS Parm='') is ignored by the assembler.
TERMINAL	TERM	
XREF	SXREF XREF	The XREF option of the JCL OPTION statement can be used to specify the XREF(FULL) assembler option. The SXREF option of the JCL OPTION statement can be used to specify the XREF(SHORT) assembler option.

## Input and output files

Depending on the options in effect, High Level Assembler requires the following files, as shown in Figure 55:




Figure 55. High Level Assembler Files

High Level Assembler requires the following files:

**SYSIPT** An input file containing the source statements to be processed.

In addition, the following six files might be required:

## Input and output files

<b>Library</b>	Library sublibraries containing macro definitions (for macro definitions not defined in the source program), source code to be called for through COPY assembler instructions, or both. One of the sublibraries may also contain a member (ASMAOPT.USER) which contains an invocation assembler option list.
<b>SYSLST</b>	A file containing the assembly listing (if the LIST option is in effect).
<b>SYSLOG</b>	A file containing flagged statements and diagnostic messages. (only if the TERM option is in effect). SYSLOG is normally assigned to the operator console.
<b>SYSPCH</b>	A file containing object module output, usually for punching (only if the DECK option is in effect).
<b>SYSLNK</b>	A file containing object module output for input to the linkage editor (only if the OBJECT option is in effect).
<b>SYSADAT</b>	A file containing associated data output (only if the ADATA option is in effect).

The files listed above are described in the text following Table 32. The characteristics of these files, those set by the assembler and those you can override, are shown in Table 32.

*Table 32. Assembler file characteristics*

File	Access Method	Logical Record Length (LRECL)	Block Size (BLKSIZE)	Record Format (RECFM)
SYSIPT	SAM	80	80	FIXED
Library	LIBR API	80	80	FIXED
Library member ASMAOPT.USER	LIBR API	80	80	FIXED
SYSLST	SAM	<b>1</b>	Same as record size	FIXED
SYSLOG	SAM	<b>2</b>	Same as record size	FIXED
SYSPCH	SAM	80	80	FIXED
SYSLNK	SAM	80	80	FIXED
SYSADAT	SAM	32756	32760	VARBLK

### Notes to Table 32:

- 1** If you specify EXIT(PRTEXT) and the user exit specifies the logical record length, the logical record length returned is used. If you do not specify EXIT(PRTEXT) or the user exit does not specify a record length, the record length is set to 121 if SYSLST is assigned to disk or 133 otherwise.  
  
The minimum record length allowed for SYSPRINT is 121, and the maximum allowed is 133.
- 2** If you specify EXIT(TRMEXIT) and the user exit specifies the logical record length, the logical record length returned is used. If you do not specify

EXIT(TRMEXIT) or the user exit does not specify a record length, the record length is set to 68. The maximum record length allowed for SYSTERM is 125.

## Specifying the source file: SYSIPT

Define the file that contains your source code with the SYSIPT ASSGN statement. If you include your source code in your job stream, it must immediately follow the EXEC statement that invokes the assembler, and be terminated with a /\* statement.

You can, however, use JCL statements to define a file that contains your source code. For example, to define a direct-access device file, use the DLBL, EXTENT, and ASSGN statements:

```
// DLBL IJSYSIN,'file-ID',0,SD
// EXTENT SYSIPT,volser,1,0,start,tracks
// ASSGN SYSIPT,DISK,VOL=volser,SHR
```

## Specifying macro and copy code libraries: LIBDEF job control statement

Include the LIBDEF job control statement if your program contains any macro calls to library macros, or any COPY instructions. LIBDEF statements define the sublibraries that contain macro definition and COPY members.

```
// LIBDEF SOURCE,SEARCH=(lib.sublib)
```

The member name in the sublibrary must match the name you specify in the macro call or COPY instruction. The member type must be A, unless the SUBLIB job control option has changed it to D. See OPTION statement description in *VSE/ESA System Control Statements* for further details.

High Level Assembler does not read edited macros (E-books). To read edited macros from the library, provide a LIBRARY user exit using the EXIT option. See “Processing E-decks” on page 233.

You don’t need the LIBDEF SOURCE statement if your assembler source code does not contain any library macro calls or COPY instructions. You also don’t need the LIBDEF SOURCE statement if the library members are in a sub-library in the permanent LIBDEF search chain.

Concatenate multiple sublibraries in the search chain if you have multiple macro or copy sublibraries.

## Specifying the listing file: SYSLST

The assembler uses this file to produce a listing. You can then direct the output to a printer, a direct access device, or a magnetic-tape device. The listing includes the results of the default or specified options of the PARM parameter (for example, diagnostic messages, the object code listing). For example:

```
// ASSGN SYSLST,PRT1
```

## Directing assembler messages to your console log: SYSLOG

If you specify the TERM assembler option, the assembler writes flagged statements and diagnostic messages to the console log.

### Specifying object code files: SYSLNK and SYSPCH

When using the OBJECT assembler option, or DECK assembler option, you can store the object code on disk or tape. The assembler uses the SYSLNK or SYSPCH files you define in your JCL to store the object code.

In the example below, the created object module is ready to be passed to the linkage editor:

```
// DLBL IJSYSLN,'file-ID',0,SD
// EXTENT SYSLNK,volser,1,0,start,tracks
// ASSGN SYSLNK,DISK,VOL=volser,SHR
```

You don't need to define SYSLNK in your JCL if the NOOBJECT option is in effect.

The following example defines SYSPCH as a direct-access device file:

```
// DLBL IJSYSPH,'file-ID',0,SD
// EXTENT SYSPCH,volser,1,0,start,tracks
ASSGN SYSPCH,DISK,VOL=volser,SHR
```

You don't need to define the SYSPCH file if the NODECK option is in effect.

### Specifying the associated data file: SYSADAT

Use the SYSADAT DLBL statement to define your associated data output file statement:

```
// DLBL SYSADAT,'HLASM.WORK.SYSADAT',0,VSAM,RECORDS=(100,100),      X
                           RECSIZE=32760,DISP=(NEW,KEEP),CAT=VSESPUC
```

The associated data file contains information about the assembly. It provides information for use by symbolic debugging and cross-reference tools. The SYSADAT file must be directed to a direct-access storage device and can be a SAM file or SAM-ESDS file.

---

## Return codes

High Level Assembler issues return codes that you can check with the IF and ON job control statements. The IF and ON job control statements let you skip or run a job step, depending on the results (indicated by the return code) of a previous job step. See *VSE/ESA System Control Statements* for details about the IF and ON job control statements.

The return code issued by the assembler is the highest severity code that is associated with any error detected in the assembly, or with any MNOTE message produced by the source program or macro instructions. The return code can be controlled by the FLAG(*n*) assembler option described on page 54. See Appendix G, "High Level Assembler messages," on page 335 for a listing of the assembler errors and their severity codes.



---

## Chapter 14. Link-editing and running your program on z/VSE

If you produce an object module when you assemble your program, it needs further processing before it can run. This further processing, the resolution of external references inserted by the assembler, is performed by the linkage editor. The linkage editor converts an object module into an executable program, which is called a *phase*.

---

### The linkage editor

The linkage editor converts an object module into a phase and catalogs it in a library sublibrary. The phase then becomes a permanent member of that sublibrary, with a member type of PHASE, and can be retrieved at any time and run in either the job that created it or any other job.

Alternatively, you can request the linkage editor to store the phase temporarily, in the virtual I/O area. The phase is then ready to run. Using this method, the linkage editor does not save a permanent copy of the phase. Consequently, after the phase has been run, it cannot be used again without creating another phase. This method is useful during testing.

---

### Creating a phase

The linkage editor processes your assembled program (object module) and prepares it for running. The processed object module becomes a phase.

Optionally, the linkage editor can process more than one object module, and transform those object modules into a single phase.

Figure 56 shows the general job control procedure for creating a phase (link-editing).

---

```
// JOB jobname
// DLBL IJSYSLN,'file-ID',0,SD
// EXTENT SYSLNK,volser,1,0,start,tracks
// ASSGN SYSLNK,DISK,VOL=volser,SHR
// LIBDEF OBJ,SEARCH=(lib.sublib)
// LIBDEF PHASE,CATALOG=(lib.sublib)
// OPTION CATAL
// ACTION MAP
// PHASE phasenam,*
:
// EXEC LNKEDT
/&
```

---

Figure 56. Sample job control for creating a phase

---

### Input to the linkage editor

Your input to the linkage editor can be:

- One or more object modules (created through the OBJECT or DECK assembler option).

## Input to the linkage editor

- Linkage editor control statements (including control statements generated using the assembler PUNCH statement).

### Inputting object modules

The main input to the linkage editor is the SYSLNK file that contains one or more separately assembled object modules, possibly with a PHASE linkage editor control statement.

Additional input to the linkage editor consists of object modules that are not part of the SYSLNK file, but are to be included in the phase.

The additional input can come from sublibraries containing other application object modules.

You can specify which sublibrary contains the additional object modules with the LIBDEF job control statement. If you have multiple sublibraries containing object modules to be included in the phase, concatenate them, as shown in the following example:

```
// LIBDEF OBJ,SEARCH=(PRD2.PROD,SALES.LIB)
```

In this case, the sublibraries PRD2.PROD and SALES.LIB are available for additional input to the linkage editor.

### Files for linkage editor processing

You need the following files for linkage editor processing. Table 33 summarizes the function, and permissible device types, for each file.

Table 33. Files used for link-editing

File	Type	Function	Permissible Device Types
SYSIPT <sup>1</sup>	Input	Additional object module input	Card reader Magnetic tape Direct access
SYSLNK	Input	Object module input, normally the output of the assembler	Direct access
SYSLST <sup>2</sup>	Output	Diagnostic messages Informative messages Linkage editor map	Printer Magnetic tape Direct access
SYSLOG	Output	Operator messages	Display console
SYSRDR	Input	Control statement input	Card reader Magnetic tape Direct access
IJSYS01 (SYS001)	Work file	Linkage editor work file	Direct access
User-specified Sublibrary	Library	Catalog sublibrary for the phase <sup>3</sup> External reference and INCLUDE statement resolution <sup>4</sup>	Direct access

#### Notes:

- <sup>1</sup> Object modules read from SYSIPT are written to SYSLNK
- <sup>2</sup> If not provided, messages are written to SYSLOG
- <sup>3</sup> Required if the phase is to be cataloged
- <sup>4</sup> Required for additional object module input

## Inputting additional object modules

You can use the INCLUDE linkage editor control statement to specify additional object modules you want included in the phase.

Code the INCLUDE statements before the EXEC statement that invokes the linkage editor:

```
// EXEC ASMA90,SIZE=ASMA90
:
:
/*
  INCLUDE ASSMPGM
  INCLUDE ASSMPGM1
// EXEC LNKEDT
/&
```

Object modules specified by the INCLUDE statement are written to SYSLNK as job control encounters the statements.

## Linkage editor control statements

In addition to object modules, input to the linkage editor includes linkage editor control statements. These statements are described in Table 34.

Table 34. Linkage editor control statements

Statement	Action	Comments
ACTION	<p>Use the ACTION statement to specify linkage editor options. The options are:</p> <ul style="list-style-type: none"> <li>• MAP—requests the linkage editor to write a linkage editor map to SYSLST.</li> <li>• NOMAP—suppresses the MAP option.</li> <li>• NOAUTO—suppresses the automatic library look up (AUTOLINK) function; the linkage editor does not attempt to resolve external references using the automatic library look-up function.</li> <li>• CANCEL—requests the linkage editor to cancel the job if a linkage editor error occurs.</li> <li>• SMAP—request the linkage editor to produce a sorted listing of CSECT names on SYSLST.</li> </ul>	<p>This statement must be the first linkage editor statement in your input stream.</p> <p>ACTION MAP is the default, if SYSLST is assigned.</p>
ENTRY	Use the ENTRY statement to specify the entry point of a phase that has multiple possible entry points.	The default entry point is the load address of the phase.
INCLUDE	Use the INCLUDE statement to include additional object modules in the phase that would not otherwise be included.	You can use the INCLUDE statement to include an object module that was cataloged with a different name to the name used in the CALL statement in your program.
PHASE	Use the PHASE statement to provide the linkage editor with a phase name.	You must provide a PHASE statement (and the job control option CATAL) if you want to catalog the phase in a library sublibrary.

For a complete description of these linkage editor control statements, see *VSE/ESA System Control Statements*.

---

## Output from the linkage editor

You can obtain a linkage editor storage map, and a listing of linkage editor diagnostics, to help you determine the reasons for particular errors in your program. To do this, use the ACTION MAP linkage editor control statement. If SYSLST is assigned, ACTION MAP is the default. You can specify ACTION NOMAP if you do not want the linkage editor to produce the storage map.

**Detecting Link-Edit Errors:** After link-editing, you receive a listing of diagnostic messages on SYSLST. Check the linkage editor map to make sure that all the object modules you expected were included.

Unresolved “weak” external references (WXTRN) can be ignored. However, all “strong” external references (EXTRN) should be resolved for a phase to run correctly.

You can find a description of linkage editor messages in *VSE/ESA Diagnostic Tools*.

---

## Running your assembled program

The general job control procedure to run a program on z/VSE is:

```
// DLBL (JCL for user-specified files)
// EXEC progname[,PARM='parameters']
:
```

---

## Chapter 15. z/VSE system services and programming considerations

This chapter describes some of the system services and program development facilities that assist you in developing your assembler program on z/VSE. It provides the following information:

- Adding definitions to a macro library.
- Saving and restoring general register contents.
- Ending program execution.
- Accessing execution parameters.
- Processing E-Decks.

---

### Adding definitions to a macro library

You can add macro definitions, and members containing assembler source statements that can be read by a COPY instruction, to a macro library. Use the LIBR utility program for this purpose. Details of this program and its control statements are contained in the applicable *System control statements* publication. The following example adds a new macro definition, NEWMAC, to the system library, PRD2.PROD.

```
// JOB CATMAC
// EXEC LIBR
ACCESS SUBLIB=PRD2.PROD
CATALOG NEWMAC.A REPLACE=YES
        MACRO
        NEWMAC &OP1,&OP2
        LCLA   &PAR1,&PAR2

        :
        MEND
/+
/*
```

The ACCESS statement specifies the sublibrary into which the macro is cataloged. The CATALOG statement specifies the member name and member type. REPLACE=YES indicates that the member is replaced if it already exists.

---

### Processing E-decks

An E-Deck refers to a macro source book of type E (or type F if SUBLIB=DF specified on OPTION statement). You can use these types of macros in your program; however, they must first be converted to source statement format. E-Decks are stored in edited format, and High Level Assembler requires that library macros be stored in source statement format.

You must use a library input exit to analyze a macro definition and, in the case of an E-Deck, call the ESERV program to change, line by line, the E-Deck definition back into source statement format.

See the section titled *Using the High Level Assembler Library Exit for Processing E-Decks* in *VSE/ESA Guide to System Functions*. This section describes how to set up the exit and how to use it.

## Operating system programming conventions

Assembler programs executing on z/VSE must follow a set of programming conventions to save and restore registers, and access execution parameters. These are described in the following sections.

### Saving and restoring general register contents

A program should save the values contained in the general registers when it starts to run and, on completion, restore these same values to the general registers. Thus, as control is passed from the operating system to a program and, in turn, to a subprogram, the status of the registers used by each program is preserved. This is done through use of the SAVE and RETURN system macro instructions.

**Saving Register Contents:** The SAVE macro instruction should be the first statement in the program. It stores the contents of registers 14, 15, and 0 through 12 in an area provided by the program that passes control. When a program is given control, register 13 contains the address of an area in which the general register contents should be saved.

If the program calls any subprograms, or uses any operating system services other than GETVIS, FREEVIS, and CDLOAD, it must first save the contents of register 13 and then load the address of an 18-fullword save area into register 13. This save area is in the program and is used by any subprograms or operating system services called by the program.

**Restoring Register Contents:** At completion, the program restores the contents of general registers 14, 15, and 0 through 12 by use of the RETURN system macro instruction (which also indicates program completion). The contents of register 13 must be restored before issuing the RETURN macro instruction.

**Example:** The coding sequence that follows shows the basic process of saving and restoring the contents of the registers. A complete discussion of the SAVE and RETURN macro instructions and the saving and restoring of registers is contained in the *VSE/ESA System Macros Reference*.

Name	Operation	Operand
BEGIN	SAVE	(14,12)
	USING	BEGIN,15
:		
	ST	13,SAVEBLK+4
	LA	13,SAVEBLK
:		
	L	13,SAVEBLK+4
	RETURN	(14,12)
SAVEBLK	DC	18F'0'
:		
	END	

### Ending program execution

You indicate completion of an assembler language source program by using the RETURN system macro instruction to pass control from the terminating program to the program that initiated it. The initiating program might be the operating system or, if a subprogram issued the RETURN, the program that called the subprogram.

In addition to indicating program completion and restoring register contents, the RETURN macro instruction can also pass a return code—a condition indicator that can be used by the program receiving control.

If the return is to the operating system, the return code is compared against the condition stated in the IF and ON job control statements.

If return is to another program, the return code is available in general register 15, and can be used as required. Your program should restore register 13 before issuing the RETURN macro instruction.

The RETURN system macro instruction is discussed in detail in the applicable application programming *Macro Reference* document.

### Accessing execution parameters

You access information in the PARM field of an EXEC statement by referring to the contents of general register 1. If you do not specify the PARM field of the JCL EXEC statement, register 1 and register 15 contain the same value on initial entry.

When control is given to the program, general register 1 contains the address of a fullword which, in turn, contains the address of the data area containing the information.

The data area consists of a halfword containing the count (in binary) of the number of information characters, followed by the information field. The information field is aligned to a fullword boundary. Figure 57 shows how the PARM field information is structured.




Figure 57. Access to PARM field





---

## **Part 5. Appendixes**



---

## Appendix A. Earlier assembler compatibility and migration

This section compares the High Level Assembler to the earlier assemblers, Assembler H Version 2 and DOS/VSE Assembler. This section can be used to determine the changes that might be required to migrate your assembler programs to High Level Assembler. This section also lists the new facilities that are available with High Level Assembler that you can use for new and existing assembler programs.

---

### Comparison of instruction set and assembler instructions

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
<b>Instruction set</b>			
S/370 instructions	Yes	Yes	Yes
z/Architecture instructions	No	No	Yes
XA instructions	No	Yes	Yes
ESA instructions	No	Yes	Yes
Vector instructions	No	Yes	Yes
DOS operation code table	No	No	The DOS operation code table is designed specifically for assembling programs previously assembled using the DOS/VSE assembler. Some machine instructions and assembler instructions are not included in this operation code table. See "OPTABLE" on page 66 for further details.
<b>Data definition statements</b>			
CCW	Yes	Yes	Yes
CCW0	No	Yes	Yes
CCW1	No	Yes	Yes
DC	Yes	Yes	Yes
DS	Yes	Yes	Yes
Symbols used in the DC or DS expression need not be defined before they are used	No	Yes	Yes
J-type Constant	No	No	Yes
Q-type Constant	No	Yes	Yes
R-type Constant	No	No	Yes
S-type Constant	No	Yes	Yes

## Comparison of instruction set and assembler instructions

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Number of nominal values for Binary and Hexadecimal constants	One	Multiple	Multiple
<b>Program control statements</b>			
ACONTROL	No	No	Yes
ADATA	No	No	Yes
CNOP	Name entry can have sequence symbol or spaces	Name entry can have any symbol or spaces	Name entry can have any symbol or spaces. Byte and boundary operands.
COPY	Nesting depth limited to 3	Nesting depth not limited	Nesting depth not limited
EQU	Value operand only	Value, length attribute and type attribute operands	Value, length attribute, type attribute, program type, and assembler type operands
END	END statement must be supplied	Multiple END statements are allowed. If the END statement is omitted, the assembler generates an END statement.	Multiple END statements are allowed. If the END statement is omitted, the assembler generates an END statement.
EXITCTL	No	No	Yes
ICTL	Yes	Yes	Yes
ISEQ	Yes	Yes	Yes
LTORG	Yes	Yes	Yes
OPSYN	No	Yes	Yes
ORG	Name entry can have sequence symbol or spaces	Name entry can have any symbol or spaces	Name entry can have any symbol or spaces. Boundary, and offset operands.
POP	No	Yes	Yes, with NOPRINT operand
PUNCH	Yes	Yes	Yes
PUSH	No	Yes	Yes, with NOPRINT operand
REPRO	Yes	Yes	Yes
<b>Listing control statements</b>			
CEJECT	No	No	Yes
EJECT	Yes	Yes	Yes

## Comparison of instruction set and assembler instructions

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
PRINT	Yes	Yes	Yes, with NOPRINT, MCALL, NOMCALL, MSOURCE, NOMSOURCE, UHEAD, and NOUHEAD operands
SPACE	Yes	Yes	Yes
TITLE	Up to 4 characters in name (if not a sequence symbol)	Up to 8 characters in name (if not a sequence symbol)	Up to 8 characters in name (if not a sequence symbol)
<b>Base register assignment</b>			
DROP	Yes	Yes	Yes
USING	Yes, ordinary USING	Yes, ordinary USING	Yes, ordinary, labeled, and dependent USINGs
<b>Program sectioning and linking</b>			
ALIAS	No	No	Yes
AMODE	No	Yes	Yes
CATTR (z/OS and CMS)	No	No	Yes
COM	Only unnamed common control sections are allowed	Yes	Yes
CSECT	Only named control sections are allowed	Yes	Yes
CXD	No	Yes	Yes
DSECT	Yes	Yes	Yes
DXD	No	Yes	Yes
ENTRY	The maximum number of symbols that can be identified by the ENTRY instruction is 200	Yes	Yes
EXTRN	Yes	Yes	Yes
PART	No	No	Yes
RMODE	No	Yes	Yes
RSECT	No	Yes	Yes, with automatic checking for reenterability
START	Only named control sections are allowed	Yes	Yes
XATTR (z/OS and CMS)	No	No	Yes

### Comparison of macro and conditional assembly statements

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
<b>Macro definition</b>			
MACRO	Yes	Yes	Yes
MEND	Yes	Yes	Yes
MEXIT	Yes	Yes	Yes
<b>Conditional assembly</b>			
ACTR	Yes	Yes	Yes
AEJECT	No	No	Yes
AGO	Yes	Yes	Yes
AIF	Yes	Yes	Yes
AINsert	No	No	Yes
ANOP	Yes	Yes	Yes
AREAD	No	Yes	Yes
ASPACE	No	No	Yes
GBLA	Yes	Yes	Yes
GBLB	Yes	Yes	Yes
GBLC	Yes	Yes	Yes
LCLA	Yes	Yes	Yes
LCLB	Yes	Yes	Yes
LCLC	Yes	Yes	Yes
MHELP	No	Yes	Yes
MNOTE	Not allowed in open code	Allowed in open code	Allowed in open code
SETA	Yes	Yes	Yes
SETB	Yes	Yes	Yes
SETC	Yes	Yes	Yes
SETAF	No	No	Yes
SETCF	No	No	Yes
<b>System variable symbols</b>			
&SYSADATA_DSN	No	No	Yes
&SYSADATA_MEMBER	No	No	Yes
&SYSADATA_VOLUME	No	No	Yes
&SYSASM	No	No	Yes
&SYSCLOCK	No	No	Yes
&SYSDATC	No	No	Yes
&SYSDATE	No	Yes	Yes
&SYSECT	Yes	Yes	Yes
&SYSIN_DSN	No	No	Yes
&SYSIN_MEMBER	No	No	Yes
&SYSIN_VOLUME	No	No	Yes

## Comparison of macro and conditional assembly statements

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
&SYSJOB	No	No	Yes
&SYSLIB_DSN	No	No	Yes
&SYSLIB_MEMBER	No	No	Yes
&SYSLIB_VOLUME	No	No	Yes
&SYSLIN_DSN	No	No	Yes
&SYSLIN_MEMBER	No	No	Yes
&SYSLIN_VOLUME	No	No	Yes
&SYSLIST	Yes	Yes	Yes
&SYSLOC	No	Yes	Yes
&SYSM_HSEV	No	No	Yes
&SYSM_SEV	No	No	Yes
&SYSMAC	No	No	Yes
&SYSNDX	Up to maximum of 9999	Up to maximum of 9999999	Up to maximum of 9999999
&SYSNEST	No	No	Yes
&SYSOPT_DBCS	No	No	Yes
&SYSOPT_OPTABLE	No	No	Yes
&SYSOPT_RENT	No	No	Yes
&SYSOPT_XOBJECT	No	No	Yes
&SYSPARM	Yes	Yes	Yes
&SYSPRINT_DSN	No	No	Yes
&SYSPRINT_MEMBER	No	No	Yes
&SYSPRINT_VOLUME	No	No	Yes
&SYSPUNCH_DSN	No	No	Yes
&SYSPUNCH_MEMBER	No	No	Yes
&SYSPUNCH_VOLUME	No	No	Yes
&SYSSEQF	No	No	Yes
&SYSSTEP	No	No	Yes
&SYSSTMT	No	No	Yes
&SYSSTYP	No	No	Yes
&SYSTEM_ID	No	No	Yes
&SYSTEM_DSN	No	No	Yes
&SYSTEM_MEMBER	No	No	Yes
&SYSTEM_VOLUME	No	No	Yes
&SYSTIME	No	Yes	Yes
&SYSVER	No	No	Yes
<b>Symbol attributes</b>			
Defined attribute	No	Yes	Yes

## Comparison of macro and conditional assembly statements

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Type attribute	An ordinary symbol outside a macro cannot be used as an operand of the T' inside a macro and cannot be used to determine the type of a SETA or SETB variable.  Only allowed in conditional assembly instructions and not allowed for literals.	Yes; only allowed in conditional assembly instructions and not allowed for literals.	Yes; allowed in conditional assembly, assembler, and machine instructions and literals.
Length attribute	Yes; allowed in conditional assembly, assembler, and machine instructions and not allowed for literals.	Yes; allowed in conditional assembly, assembler, and machine instructions and not allowed for literals.	Yes; allowed in conditional assembly, assembler, and machine instructions and literals.
Scaling attribute	Yes; only allowed in conditional assembly instructions and not allowed for literals.	Yes; only allowed in conditional assembly instructions and not allowed for literals.	Yes; allowed in conditional assembly, assembler, and machine instructions and literals.
Integer attribute	Yes; only allowed in conditional assembly instructions and not allowed for literals.	Yes; only allowed in conditional assembly instructions and not allowed for literals.	Yes; allowed in conditional assembly, assembler, and machine instructions and literals.
Count attribute	Can only be used to determine the length of a macro instruction operand	Yes	Yes
Number attribute	Yes	Can be applied to SETx variables	Can be applied to SETx variables
Operation Code Data attribute	No	No	Yes
Type and Count attribute for system variable symbols	No	Yes	Yes
Type attribute for SETA symbols that are defined via LCLA or GBLA but are not set (via SETA)	Not applicable	Returns a value of '00'	Returns a value of 'N'
Type attribute for SETB symbols that are defined via LCLB or GBLB but are not set (via SETB)	Not applicable	Issues an error message	Returns a value of 'N'
Type attribute for macro instruction operands with a value of a previously used literal	Not applicable	Returns a value of 'U'	Returns the Type attribute of the constant defined by the literal



## Comparison of macro and conditional assembly

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
External Function calls using high level programming language	No	No	Yes
Built-In Functions for SETA, SETB, and SETC expressions	No	No	Yes
Substring length value	No	No	Yes
The second subscript value of the substring notation can be specified as an (*).			
Library macros in source format	No, library macros must be stored in edited format	Yes	Yes
Macro definitions can appear anywhere in your source module.	No, they must be at the start of the source file.	Yes	Yes
Editing macro definitions	No	Yes	Yes
Use conditional assembly statement to avoid editing of macros.			
Redefining macros	No	Yes	Yes
A macro definition can be redefined at any point in the source code.			
Nesting macro definitions	No	Yes	Yes
Allow inner macro definitions.			
Generated macro instruction operation codes	No	Yes	Yes
Macro instruction operation codes can be generated by substitution.			
Multilevel sublists in macro instruction operands	No	Yes	Yes
Multilevel sublists (sublists within sublists) are permitted in macro instruction operands and in keyword default values in prototype statements.			
DBCS language support	No	Yes	Yes
Double-byte data is supported by the macro language.			
Macro names, variable symbols (including the ampersand) and sequence symbols (including the period) can be up to a maximum of 63 characters.	No, limited to 8 characters	Yes	Yes
Comments (both ordinary comments beginning with '*' and internal macro comments beginning with '.*') can be inserted between the macro header and the prototype and, for library macros, before the macro header.	No	Yes	Yes
Any mnemonic operation code, or any assembler operation code, can be defined as a macro instruction.	No	Yes	Yes

## Comparison of macro and conditional assembly

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Any instruction, except ICTL, is permitted within a macro definition.	No	Yes	Yes
AIF statements	No	Yes	Yes
The AIF statement can include a string of logical expressions and related sequence symbols.			
AGO statements	No	Yes	Yes
The AGO statement can contain computed branch sequence information.			
SETx statements	No	Yes	Yes
The SETA, SETB and SETC statements can assign lists or arrays of values to subscripted SET symbols.			
SET symbol format and definition changes	No	Yes	Yes
<ul style="list-style-type: none"> <li>A macro definition or open code can contain more than one declaration for a given SET symbol, as long as only one is encountered during a given macro expansion or conditional assembly.</li> <li>A SET symbol that has not been declared in a LCLx or GBLx statement is implicitly declared by appearing in the name field of a SETx statement.</li> <li>A SET symbol can be defined as an array of values by adding a subscript after it, when it is declared, either explicitly or implicitly.</li> </ul>			
Created SET symbols	No	Yes	Yes
SET symbols may be created during the generation of a macro.			
Using SETC variables in arithmetic expressions	No	Yes	Yes
You can use a SETC variable as an arithmetic term if its character string value represents a valid self-defining term.			
Forward attribute references	No	Yes	Yes
If an attribute reference is made to a symbol that has not yet been encountered, the assembler scans the source code either until it finds the referenced symbol in the name field of a statement in open code, or until it reaches the end of the source module.			
Attribute reference using SETC variables	No	Yes	Yes
<p>You can take an attribute reference for a symbol specified as:</p> <ul style="list-style-type: none"> <li>The name of the ordinary symbol itself</li> <li>The name of a symbolic parameter whose value is the name of the ordinary symbol</li> <li>The name of a SETC symbol whose value is the name of the ordinary symbol</li> </ul>			

## Comparison of macro and conditional assembly

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Number attributes for SET symbols	No	Yes	Yes
The number attribute can be applied to SETx variables to determine the highest subscript value of a SET symbol array to which a value has been assigned in a SETx instruction.			
Alternate format in conditional assembly	No	Yes	Yes
The alternate format allows a group of operands to be spread over several lines of code.			
Maximum number of symbolic parameters and macro instruction operands	200	No fixed maximum	No fixed maximum
Mixing positional and keyword symbolic parameters and macro instruction operands	All positional parameters or operands must come first.	Keyword parameters or operands can be interspersed among positional parameters or operands.	Keyword parameters or operands can be interspersed among positional parameters or operands.
SET symbol declaration	Declaration of local symbols must immediately precede declaration of global symbols.	Declaration of local and global symbols can be mixed.	Declaration of local and global symbols can be mixed.
	Declaration of global and local symbols must immediately follow prototype statement if in macro definition.	Declaration of global and local symbols does not need to immediately follow prototype statement if in macro definition.	Declaration of global and local symbols does not need to immediately follow prototype statement if in macro definition.
	Declaration of global and local symbols must immediately follow source macro definitions, if in open code.	Declaration of global and local symbols does not need to immediately follow source macro definitions, if in open code.	Declaration of global and local symbols does not need to immediately follow source macro definitions, if in open code.
Maximum dimension for subscripted SET Symbols	4095	Not limited	Not limited
Duplication factor allowed in SETC instruction	No	Yes	Yes
Dynamically extended SET symbol arrays	No	Yes	Yes
Number of terms in arithmetic expressions in conditional assembly	Up to 16	Not limited	Not limited
Levels of parentheses in arithmetic expressions in conditional assembly	Up to 5	Not limited	Not limited
MNOTE with error in macro is flagged at each invocation	Yes	No	No
Blank lines treated as equivalent to ASPACE 1.	No	No	Yes
Name entry of macro instruction must be a valid symbol	Yes	Yes	No
Ampersand preceding the SET symbols being declared is optional	No	No	Yes

## Comparison of macro and conditional assembly

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Predefined absolute symbols allowed in arithmetic expression	No	No	Yes
Predefined absolute symbols allowed in SETx instruction	No	No	Yes
Type attribute of CNOP Label is set to 'I'	No, set to 'J'	No, set to 'J'	Yes
Length, scaling and integer attribute allowed for ordinary symbols, SETC symbols and literals in open code	No	No	Yes
Sublists assigned to SETC symbols can be passed to macro definitions and be recognized as sublists	No	No	Yes

## Comparison of language features

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Macro comment statements allowed in open code	No	No	Yes
EQU instruction extension			
Symbols appearing in the first operand of the EQU instruction need not have been previously defined.	No	Yes	Yes, program type and assembler type operands
	No	No	Yes
Operands for assembler and program types.			
CNOP instruction extension			
There is no restriction that symbols in the operand field of a CNOP instruction must have been previously defined.	No	Yes	Yes, byte and boundary operands
	No	No	Yes
Support for quadword alignment.			
COPY instruction extension	No, nesting depth limited to 3	Yes	Yes
Any number of 'nestings', COPY statements within code that have been brought into your program by another COPY statement, is permitted.			
COPY instruction processed immediately	No, AFILE is never opened, read from, or processed in any way.	Yes, AFILE is scanned during lookahead processing	Yes, AFILE is scanned during lookahead processing
COPY members are read immediately after a COPY statement is encountered in the source, regardless of whether or not conditional processing requires it, as in the following example:			
<pre> AGO    .LABEL COPY   AFILE .LABEL ANOP </pre>			

## Comparison of language features

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
COPY instruction operand can, in open code, be specified as a variable symbol.	No	No	Yes
ISEQ instruction extension	No	Yes	Yes
Sequence checking of any column on input records is allowed.			
Macro names	No	Yes	Yes
Inline macro names may contain the underscore character (_).			
Continuation lines	Up to 2	Up to 9	Up to 9
Continuation lines and double-byte data	No	Yes	Yes
Symbol name length up to 63 characters	No, limited to 8	Yes	Yes
Levels within expressions	No	Yes	Yes
Any number of terms or levels of parenthesis in an expression is allowed.			
Underscores in symbols	No	Yes	Yes
You can specify the underscore character (_) in ordinary symbols and variable symbols.			
Underscore character accepted in any position in symbol name	No	No	Yes
Underscore character accepted in external symbols	No	No	Yes
Underscore character accepted in name field of OPSYN instruction	No	No	Yes
Maximum number of external symbols	511	65 535	65 535
DBCS language support	No	Yes	Yes
Pure double-byte data, and double-byte data mixed with single-byte data is permitted.			
Location counter value printed for EQU, USING, ORG (in ADDR2 field)	3 bytes	4 bytes (up to 3 leading zeros suppressed).	4 bytes (up to 3 leading zeros suppressed).
Self-defining term			
Maximum value	$2^{24}-1$	$2^{31}-1$	$2^{31}-1$
Number of digits			
Binary:	24	31	31
Decimal:	8	10	10
Hexadecimal:	6	8	8
Characters:	3	4	4
Relocatable and absolute expressions			
• Value carried:	Truncated to 24 bits	Truncated to 31 bits	Truncated to 31 bits
• Number of operators:	15	Not limited	
• Levels of parenthesis:	5	Not limited	Not limited Not limited
All control sections initiated by a CSECT start at location 0 in listing and object module.	Yes	No	Controlled by THREAD option

## Comparison of language features

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Copy files read once	Copy files read when statement is found	Copy files read when macro is edited (only once)	Copy files read when macro is edited (only once)
Operand greater than 1024 characters when SUBLIST	Error diagnostic with message and return code of 8	Error diagnostic with message and return code of 12	No
Remarks generated because of generated blanks in operand field	No	Yes	Yes
Blank lines treated as equivalent to SPACE 1.	No	No	Yes
Literals usable as relocatable terms in expressions	No	No	Yes
Literals usable in RX format instructions in which index register is used	No	No	Yes
Mixed case input	No	No	Yes
2-byte relocatable address constants	No	No	Yes
Multi-level PUSH supported For example, PUSH USING,USING	No	Yes. Not documented.	No

## Comparison of assembler options

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
*PROCESS statements	No	No	Selected assembler options can be specified in the source program on *PROCESS statements.
ADATA	No	No	Yes
ALIGN	Yes	Yes	Yes
ASA (z/OS and CMS)	No	No	Yes
BATCH	No	Yes	Yes
CODEPAGE	No	No	Yes
COMPAT	No	No	Yes
DBCS	No	Yes	Yes
DECK	Yes	Yes	Yes
DISK (CMS)	No	Yes	Yes
DXREF	No	No	Yes
EDECK	Yes	No	No
ERASE (CMS)	No	No	Yes
ESD	Yes	Yes	Yes
EXIT	No	No	Yes

## Comparison of assembler options

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
FLAG	No	Yes	FLAG( <i>integer</i> ), FLAG(ALIGN), FLAG(CONT), FLAG(IMPLEN), FLAG(PAGE0), FLAG(PUSH), FLAG(RECORD), FLAG(SUBSTR), and FLAG(USING0) can be specified.
FOLD	No	No	Yes
GOFF (z/OS and CMS)	No	No	Yes
INFO	No	No	Yes
LANGUAGE	No	No	Yes. Applies to messages and listing headings.
LIBMAC	No	No	Yes
LINECOUNT	Yes	Yes	Yes
LINK	Yes	No	No, see OBJECT option
LIST	Yes	Yes	LIST(121), LIST(133), and LIST(MAX) can be specified (z/OS and CMS)
MCALL	Yes	No	No; PCONTROL(MCALL) can be specified.
MXREF	No	No	MXREF(SOURCE), MXREF(XREF), and MXREF(FULL) can be specified.
NOPRINT (CMS)	No	No	Yes
NOSEG (CMS)	No	No	Yes
NUM	No	Yes (CMS)	No
OBJECT	Yes	Yes	Yes
OPTABLE	No	No	Yes
PCONTROL	No	No	Yes
PESTOP	No	No	Yes
PRINT (CMS)	No	Yes	Yes
PROFILE	No	No	Yes
RA2	No	No	Yes
RENT	No	Yes	Yes
RLD	Yes	Yes	Yes
RXREF	No	No	Yes
SEG (CMS)	No	No	Yes
SECTALGN	No	No	Yes
SIZE	No	No	Yes
STMT (z/OS and CMS)	No	Yes (CMS)	No

## Comparison of assembler options

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
SUBLIB(AE/DF) (z/VSE)	Yes. Specify on //OPTION statement.	No	Yes
SUPRWARN	No	No	Yes
SYSARM	Yes	Yes	Yes
SXREF	Yes	Same as XREF(SHORT)	Same as XREF(SHORT)
TERM	No	Yes	TERM(WIDE) and TERM(NARROW) can be specified.
TEST	No	Yes	Yes
THREAD	No	No	Yes
TRANSLATE	No	No	Yes
TYPECHECK	No	No	Yes
USING	No	No	Yes
WORKFILE	No	No	Yes
XOBJECT (z/OS and CMS)	No	No	Yes
XREF	Same as XREF (LONG)	XREF(SHORT) or XREF(LONG)	XREF(SHORT), XREF(FULL), and XREF(UNREFS) can be specified.

## Comparison of assembler listing

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Mixed case listing headings	No	No	Headings can be in mixed case English or uppercase English. See LANGUAGE assembler option.
National Language Support	No	No	Diagnostic messages in English, German, Japanese, and Spanish.
Option summary	At end of listing in Diagnostic and Statistics section.	At end of listing in Diagnostic and Statistics section.	At start of listing.
External symbol dictionary	Yes	Yes	Yes
Dummy section dictionary	Yes	No	See DSECT Cross Reference
Source and object program	Yes	Yes	Yes



## Comparison of assembler listing

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
• Page-break handling	Limited logic	Limited logic	Improved page-break handling in conjunction with the CEJECT, EJECT, SPACE, and TITLE assembler instructions, to prevent unnecessary blank pages.
• Optional 133-character wide format with extended addresses	No	No	Yes. Required for GOFF/XOBJECT.
• Control section headings	No	No	Show current control section type in fixed heading line for COM section, CSECT, DSECT, and RSECT.
• Heading date includes century	No	No	Yes
• Active USING Summary	No	No	Yes
• PRINT instruction with MCALL option	No	No	Yes
• PRINT instruction with MSOURCE option	No	No	Yes
• PRINT instruction with NOGEN option shows object code for first instruction generated, or the first 8 bytes of data generated, in the <i>object code</i> column.	No	No	Yes
• PRINT, PUSH and POP instructions with NOPRINT option	No	No	Yes
• AREAD instruction with NOPRINT option	No	No	Yes
<b>Relocation dictionary</b>	Yes	Yes	Yes
<b>Ordinary symbol and literal cross reference</b>	Yes	Yes	Yes
• Cross reference includes modification and branch flags, USING and DROP flags, EXecute instruction flag, and relocatability-type column.	No	No	Yes
<b>Unreferenced symbols defined in CSECTs</b>	No	No	Yes
<b>Macro and copy code source summary</b>	No	No	Yes
<b>Macro and copy code cross reference</b>	No	No	Yes
<b>DSECT cross reference</b>	No	No	Yes
<b>USING map</b>	No	No	Yes
<b>General purpose register cross reference</b>	No	No	Yes
<b>Diagnostic cross reference and assembler summary</b>	Diagnostic and Statistics section including error diagnostic messages	Yes	Yes
• Flagged statements with input data set information	No	No	Yes, if FLAG(RECORD) assembler option specified
• Print line with current PTF level of assembler	No	No	Yes

## Comparison of assembler listing

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
• Print line showing operating system, jobname, stepname and procedure stepname of assembly job	No	No	Yes
• Print lines showing file names (data set names), member and volume serial numbers of each of the input and output data sets	No	No	Yes
• Print lines showing statistics for external functions and external function calls	No	No	Yes
• Print lines showing statistics for I/O exits	No	No	Yes
• Print lines showing suppressed message summary	No	No	Yes
• Print line showing the amount of storage in the buffer pool	No	No	Yes
• Record counts show the number of file reads and writes	No	No	Yes
• Print line showing the return code of the assembly	No	No	Yes
• Print lines showing assembly start and stop time, and processor time	No	No	Yes
<b>Terminal output</b>	No	Yes	Yes
• Multiple consecutive spaces compressed to a single space	No	No	Yes, when TERM(NARROW) specified.
• One-line summary	No	No	Yes

## Comparison of diagnostic features

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Error messages for conflicting assembler options	No	No	Yes
When conflicting assembler options are specified, such as OBJECT with NOOBJECT, the assembler issues warning messages.			
Diagnostic information message	No	No	Yes
The FLAG(RECORD) assembler option causes message ASMA435I to be printed after the last diagnostic message for each statement in error. The message shows the statement relative record number and where the statement in error was read from.			
Statement continuation errors	No	No	Yes
The FLAG(CONT) assembler option instructs the assembler to issue diagnostic messages ASMA430W through ASMA433W when it suspects a continuation error in a macro call instruction.			

## Comparison of diagnostic features

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
Suppress alignment error messages	No	No	Yes
The FLAG(ALIGN) assembler option instructs the assembler to issue diagnostic messages ASMA033I when an alignment error is detected. This message may be suppressed by specifying the FLAG(NOALIGN) assembler option.			
Error messages	No	Yes	Yes
Error messages are printed in the listing and a summary at the end lists a total of the errors and a table of their line numbers.			
Diagnostic messages in macro assembly	No	Yes	Yes
More descriptive diagnostic error messages are printed in macro generated text.			
Sequence field in macro-generated text	No	Yes	Yes
The sequence field (columns 73 through 80) of the generated statements contains the level of the macro call, a hyphen, and the first five characters of the macro-definition name.			
Format of macro-generated text	No	Yes	Yes
Wherever possible, a generated statement is printed in the same format as the corresponding macro definition (model) statement.			
Error messages for a library macro definition	No	Yes	Yes
Format errors within a particular library macro definition are listed directly following the first call of that macro.			
Error messages for source program macro definition	No	Yes	Yes
Macro definitions contained in the source program are printed in the listing, provided the applicable PRINT options are in effect.			
Error messages in macro-generated text	No	Yes	Yes
Diagnostic messages in generated text generally include a description of the error, the recovery action, model statement number at which the error occurred, and a SET symbol name, parameter number, or a value associated with the error.			
Macro Trace Facility (MHELP)	No	Yes	Yes
Suppression of warning messages	No	No	Yes
The SUPRWARN assembler option instructs the assembler to suppress specified diagnostic messages of severity 4 or less.			
Instruction operand type checking	No	No	Yes

## Other assembler differences

Element	DOS/VSE Assembler	Assembler H Version 2	High Level Assembler
<b>Object module</b>			
DXD, CXD and Q-type constants produced	No	Yes	Yes
Named COMMON	No	Yes	Yes
Unnamed CSECTS (private code)	No	Yes	Yes
SYM records produced	No	Yes	Yes
Generalized object format module generation (z/OS and CMS)	Not applicable	No	Yes. Refer to GOFF/XOBJECT assembler option.
I Support for relative-immediate external references	No	No	Yes
<b>Diagnostics</b>			
Diagnostic messages issued	At end of assembly	At line where error occurred if possible.	At line where error occurred if possible.
Diagnostic dump	No	Produced at time of failure	Produced at time of failure
Error diagnostics messages in mixed case	No	No	Yes
<b>Resources</b>			
Work file	3 Work Files	1 Work File	No. Tolerated if allocated, but not used.
Associated data file	No	No	Yes
QSAM Input/output (z/OS and CMS)	Not applicable	No	Yes
External functions	No	No	Yes
Input/Output user exits	No	No	Yes
System-Determined Blocksize (z/OS)	Not applicable	No	Yes; supported in z/OS only.
31-bit-addressable storage exploited during assembly	No	No	Yes; does not include I/O buffers.
Minimum virtual storage requirements	200K	200K	610K
Printer control characters (z/OS and CMS)	American National Standard	Machine	American National Standard or machine depending on ASA option
Alternative assembler option sourcefile	No	No	Yes

---

## Appendix B. Cross-system portability considerations

This section describes the issues you must consider when you use High Level Assembler to assemble a program under one operating system and execute the resulting program under another operating system.

---

### Using machine instructions

High Level Assembler supports assembly of programs using z/Architecture instructions, Extended Architecture instructions, Enterprise System Architecture instructions, and Vector instructions, under all operating systems supported by High Level Assembler.

A generated object program using a specified set of instructions can only run on a processor under an operating system that provides the necessary architecture support for the instructions used.

---

### Using system macros

Many system macros have the same name under different systems, but generate different object code and have different parameters. For example, the OPEN, CLOSE, GET, and PUT macros have the same name on z/OS and z/VSE but generate different object code.

Wherever the assembled program uses system macros, the system macros for the target system must be used when the program is assembled.

For example, when the assembled program is to be run under z/VSE, the z/VSE system macros must be used, even if the program is assembled under CMS.

Ensure that the macros used during assembly are for the correct release of the operating system upon which the assembled program is to run.

---

### Migrating object programs

The object module produced by High Level Assembler is portable across all the supported operating systems (but GOFF object files are not portable to z/VSE). Therefore, an assembler program may be assembled under any of the supported operating systems and run under any of the supported operating systems. For example, an assembler program may be assembled under CMS and run under z/VSE if the appropriate macro libraries are used for assembling the program.

The object module is portable across the supported operating systems with the following restrictions:

- Wherever the assembler program uses system macros, the system macros for the target system must be used.
- The object module must be link-edited using the target system linkage editor.
- The assembler instructions included in the assembler program must be supported by the system linkage editor.

The z/VSE linkage editor, prior to VSE/ESA Version 2 Release 1, does not support dummy external DSECTS. Therefore, to link-edit the assembler program

## Migrating object programs

under earlier VSE operating systems, the assembler program must not include any DXD or CXD statements or Q-type address constants.

- The TEST assembler option should only be used if the object module is to be link-edited under z/OS.

### z/VM and z/OS

The TEST option cannot be specified with the GOFF assembler option, which produces the generalized object format module.

### End of z/VM and z/OS

- A generalized object format module cannot be ported to a z/VSE or CMS environment.
- Some enhancements such as external relative-immediate references and quadword-aligned control sections may not be supported on some z/VM and z/VSE systems.

---

## Appendix C. Object deck output

High Level Assembler produces the object module when you specify either the OBJECT or DECK assembler option.

The object module consists of 80-byte records with 5 record types. The record types are:

**ESD** External symbol dictionary records describe the external symbols used in the program.

**TXT** Text records describe object code generated.

**RLD** Relocation dictionary records provide the information required to relocate address constants within the object module.

**END** End records terminate the object module and optionally provide the entry point.

**SYM** Symbol table records provide symbol information for TSO TEST.

**Note:** If you have specified the GOFF assembler option, High Level Assembler produces the object module in Generalized Object File format (GOFF). For more information on GOFF, refer to *z/OS MVS Program Management: Advanced Facilities*.

The assembler can also produce records via the PUNCH and REPRO assembler statements, whose contents and format are entirely determined by the program.

The following sections describe the format of each record type.

---

### ESD record format

Columns	Contents										
1	X'02'										
2–4	ESD										
5–10	Space										
11–12	Variable field count—number of bytes of information in variable field (columns 17–64)										
13–14	Space										
15–16	ESDID of first SD, XD, CM, PC, ER, or WX in variable field; blank for LD items, which have the ESDID of the preceding SD. This field is blank if all items are LD.										
17–64	Variable field. One-to-three 16-byte items of the following format: <ul style="list-style-type: none"><li>• 8-byte external symbol name</li><li>• 1-byte ESD type code:</li></ul> <table><tr><th>Hex Value</th><th>ESD Type Code</th></tr><tr><td>00</td><td>SD</td></tr><tr><td>01</td><td>LD</td></tr><tr><td>02</td><td>ER</td></tr><tr><td>04</td><td>PC</td></tr></table>	Hex Value	ESD Type Code	00	SD	01	LD	02	ER	04	PC
Hex Value	ESD Type Code										
00	SD										
01	LD										
02	ER										
04	PC										

|  
|  
|

<b>05</b>	CM
<b>06</b>	XD(PR)
<b>0A</b>	WX
<b>0D</b>	Quad-aligned SD
<b>0E</b>	Quad-aligned PC
<b>0F</b>	Quad-aligned CM

- 3-byte address
- 1-byte flag:
  - Alignment if XD
  - Space if LD, ER, or WX
  - AMODE/RMODE flags if SD, PC, or CM. Table 35 describes the AMODE and RMODE flag values.

*Table 35. AMODE/RMODE flags*

Bits	Value	Description
2	0	Use the RMODE bit (bit 5)
	1	RMODE 64
3	0	Use the AMODE bits (bits 6-7)
	1	AMODE 64
4	1	RSECT
5	0	RMODE 24
	1	RMODE 31, RMODE ANY
6–7	00	AMODE 24
	01	AMODE 24
	10	AMODE 31
	11	AMODE ANY

- 3-byte length, LDID, or space

#### **Variable field item 1**

<b>17–24</b>	External symbol name
<b>25</b>	ESD type code
<b>26–28</b>	Address
<b>29</b>	Flag
<b>30–32</b>	Length, LDID, or space

#### **Variable field item 2**

<b>33–40</b>	External symbol name
<b>41</b>	ESD type code
<b>42–44</b>	Address
<b>45</b>	Flag
<b>46–48</b>	Length, LDID, or space

#### **Variable field item 3**

<b>49–56</b>	External symbol name
<b>57</b>	ESD type code
<b>58–60</b>	Address
<b>61</b>	Flag
<b>62–64</b>	Length, LDID, or space
<b>65–72</b>	Space

**73–80** Deck ID, sequence number, or both. The deck ID is the name from the first TITLE statement that has a non-spaces name field. This



name can be 1–8 characters. If the name is fewer than 8 characters or if there is no name, the remaining columns contain a record sequence number.

---

## TXT record format

Columns	Contents
1	X'02'
2–4	TXT
5	Space
6–8	Relative address of first instruction on record
9–10	Space
11–12	Byte count—number of bytes in information field (columns 17–72)
13–14	Space
15–16	ESDID
17–72	56-byte information field
73–80	Deck ID, sequence number, or both. The deck ID is the name from the first TITLE statement that has a non-spaces name field. The name can be 1–8 characters. If the name is fewer than 8 characters or if there is no name, the remaining columns contain a record sequence number.

---

## RLD record format

Columns	Contents																												
1	X'02'																												
2–4	RLD																												
5–10	Space																												
11–12	Data field count—number of bytes of information in data field (columns 17–72)																												
13–16	Space																												
17–72	Data field: <table> <tr> <td>17–18</td><td>Relocation ESDID</td></tr> <tr> <td>19–20</td><td>Position ESDID</td></tr> <tr> <td>21</td><td>Flag byte. Describes the type of relocation required:               <table> <tr> <td>Bit 0</td><td>Reserved</td></tr> <tr> <td>Bit 1</td><td>If 1, add 4 to address constant length</td></tr> <tr> <td>Bit 2–3</td><td>Address constant type:                   <table> <tr> <td>0</td><td>A</td></tr> <tr> <td>1</td><td>V</td></tr> <tr> <td>2</td><td>Q</td></tr> <tr> <td>3</td><td>CXD</td></tr> </table> </td></tr> <tr> <td>Bits 4–5</td><td>Address constant length minus 1</td></tr> <tr> <td>Bit 6</td><td>Direction of relocation (0 for +, 1 for –)</td></tr> <tr> <td>Bit 7</td><td>If 1, the same P-ID and R-ID for the next RLD item</td></tr> </table> </td></tr> <tr> <td>22–24</td><td>Absolute address to be relocated</td></tr> </table>	17–18	Relocation ESDID	19–20	Position ESDID	21	Flag byte. Describes the type of relocation required: <table> <tr> <td>Bit 0</td><td>Reserved</td></tr> <tr> <td>Bit 1</td><td>If 1, add 4 to address constant length</td></tr> <tr> <td>Bit 2–3</td><td>Address constant type:                   <table> <tr> <td>0</td><td>A</td></tr> <tr> <td>1</td><td>V</td></tr> <tr> <td>2</td><td>Q</td></tr> <tr> <td>3</td><td>CXD</td></tr> </table> </td></tr> <tr> <td>Bits 4–5</td><td>Address constant length minus 1</td></tr> <tr> <td>Bit 6</td><td>Direction of relocation (0 for +, 1 for –)</td></tr> <tr> <td>Bit 7</td><td>If 1, the same P-ID and R-ID for the next RLD item</td></tr> </table>	Bit 0	Reserved	Bit 1	If 1, add 4 to address constant length	Bit 2–3	Address constant type: <table> <tr> <td>0</td><td>A</td></tr> <tr> <td>1</td><td>V</td></tr> <tr> <td>2</td><td>Q</td></tr> <tr> <td>3</td><td>CXD</td></tr> </table>	0	A	1	V	2	Q	3	CXD	Bits 4–5	Address constant length minus 1	Bit 6	Direction of relocation (0 for +, 1 for –)	Bit 7	If 1, the same P-ID and R-ID for the next RLD item	22–24	Absolute address to be relocated
17–18	Relocation ESDID																												
19–20	Position ESDID																												
21	Flag byte. Describes the type of relocation required: <table> <tr> <td>Bit 0</td><td>Reserved</td></tr> <tr> <td>Bit 1</td><td>If 1, add 4 to address constant length</td></tr> <tr> <td>Bit 2–3</td><td>Address constant type:                   <table> <tr> <td>0</td><td>A</td></tr> <tr> <td>1</td><td>V</td></tr> <tr> <td>2</td><td>Q</td></tr> <tr> <td>3</td><td>CXD</td></tr> </table> </td></tr> <tr> <td>Bits 4–5</td><td>Address constant length minus 1</td></tr> <tr> <td>Bit 6</td><td>Direction of relocation (0 for +, 1 for –)</td></tr> <tr> <td>Bit 7</td><td>If 1, the same P-ID and R-ID for the next RLD item</td></tr> </table>	Bit 0	Reserved	Bit 1	If 1, add 4 to address constant length	Bit 2–3	Address constant type: <table> <tr> <td>0</td><td>A</td></tr> <tr> <td>1</td><td>V</td></tr> <tr> <td>2</td><td>Q</td></tr> <tr> <td>3</td><td>CXD</td></tr> </table>	0	A	1	V	2	Q	3	CXD	Bits 4–5	Address constant length minus 1	Bit 6	Direction of relocation (0 for +, 1 for –)	Bit 7	If 1, the same P-ID and R-ID for the next RLD item								
Bit 0	Reserved																												
Bit 1	If 1, add 4 to address constant length																												
Bit 2–3	Address constant type: <table> <tr> <td>0</td><td>A</td></tr> <tr> <td>1</td><td>V</td></tr> <tr> <td>2</td><td>Q</td></tr> <tr> <td>3</td><td>CXD</td></tr> </table>	0	A	1	V	2	Q	3	CXD																				
0	A																												
1	V																												
2	Q																												
3	CXD																												
Bits 4–5	Address constant length minus 1																												
Bit 6	Direction of relocation (0 for +, 1 for –)																												
Bit 7	If 1, the same P-ID and R-ID for the next RLD item																												
22–24	Absolute address to be relocated																												

## RLD record format

25–72 Remaining RLD entries

73–80 Deck ID, sequence number, or both. The deck ID is the name from the first TITLE statement that has a non-spaces name field. The name can be 1–8 characters or if there is no name, the remaining columns contain a record sequence number.

If the rightmost bit of the flag byte is set, the following RLD entry has the same relocation ESDID and position ESDID, and this information is not repeated; if the rightmost bit of the flag byte is not set, the next RLD entry has a different relocation ESDID or position ESDID, and both ESDIDs are recorded.

Note that certain combinations in the Flag byte are used to indicate Relative-Immediate relocation items:

B'x111 00xx' 2-byte Relative-Immediate reference  
B'x111 10xx' 4-byte Relative-Immediate reference

The first RLD item on each RLD record must specify the Relocation and Position ESDIDs; thus, the last RLD item on a record may not set the rightmost bit of the flag byte.

For example, if the RLD entries 1, 2, and 3 of the program listing contain the following information:

Entry	Position ESDID	Relocation ESDID	Flag	Address
1	02	04	0C	000100
2	02	04	0C	000104
3	03	01	0C	000800

then columns 17–72 of the RLD record would be:

Column:	Entry 1								Entry 2								Entry 3															
	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	39	40	41	42	43	44	45	46	47	48
	00	04	00	02	00	00	01	00	0C	00	01	04	00	01	00	03	0C	00	08	00												
	ESD Ids				Address				Address				ESD Ids				Address				Spaces											
					↑				↑								↑															
					Flag (Set)				Flag (not set)								Flag (not set)															

## END record format

### Columns

#### Contents

1	X'02'
2–4	END
5	Space
6–8	Entry address from operand of END record in source deck (blank if no operand)
9–14	Space
15–16	For a Type 1 END record: ESDID of entry point

	For a Type 2 END record: Blank
17–24	For a Type 1 END record: Blank
	For a Type 2 END record: Symbolic entry point name if specified, otherwise blank
25–28	Blank
29–32	Control section length for a CSECT whose length was not specified on its SD ESD item. Byte 29 is zero if this length field is present. (Blank field if not present.)
33	Number of IDR items that follow (EBCDIC 1 or EBCDIC 2), or blank if none
34–52	Translator identification, version and release level (such as 0101), and date of the assembly (yyddd)
53–71	When present, they are the same format as columns 34–52
72	Space
73–80	Deck ID, sequence number, or both. The deck ID is the name from the first TITLE statement that has a non-spaces name field. The name can be 1–8 characters. If the name is fewer than 8 characters or if there is no name, the remaining columns contain a record sequence number.

---

## SYM record format

If you request it, the assembler writes out symbolic information concerning the assembled program ahead of all other object module records. The format of the output record images is as follows:

Columns	Contents
1	X'02'
2–4	SYM
5–10	Space
11–12	Variable field—number of bytes of text in variable field (columns 17–72)
13–16	Space
17–72	Variable field (see below)
73–80	Deck ID, sequence number, or both. The deck ID is the name from the first TITLE statement that has a non-space name field. The name can be 1–8 characters. If the name is fewer than 8 characters or if there is no name, the remaining columns contain a record sequence number.

The variable field (columns 17–72) contains up to 56 bytes of text. The items comprising the text are packed together; consequently, only the last record may contain less than 56 bytes of text in the variable field. The formats of a text record and an individual text item are shown in Figure 58 on page 265. The contents of the fields within an individual entry are as follows:

## SYM record format

1. Organization (1 byte). The possible values are shown in Table 36.

Table 36. Organization value byte

Bits	Value	Description
0	0	Non-data type
	1	Data type
1–3 If non-data type	000	Space
	001	Control section
	010	Dummy control section
	011	Common
	100	Instruction
	101	CCW, CCW0, CCW1
1 If data type	0	No multiplicity
	1	Multiplicity (indicates presence of M Field)
2 If data type	0	Independent (not a packed or zoned decimal constant)
	1	Cluster (packed or zoned decimal constant)
3 If data type	0	No scaling
	1	Scaling (indicates presence of S field)
4	0	Name present
	1	Name not present
5–7		Length of name minus 1

2. Address (3 bytes)—displacement from base of control section
3. Symbol Name (0–8 bytes)—symbolic name of particular item. If the entry is non-data type and space, an extra byte is present that contains the number of bytes that have been skipped.
4. Data Type (1 byte)—contents in hexadecimal
  - 00 = character
  - 04 = hexadecimal or pure DBCS (G-type)
  - 08 = binary
  - 10 = fixed point, full
  - 14 = fixed point, half
  - 18 = floating point, short
  - 1C = floating point, long
  - 20 = A-type or Q-type data
  - 24 = Y-type data
  - 28 = S-type data
  - 2C = V-type data
  - 30 = packed decimal
  - 34 = zoned decimal
  - 38 = floating point, extended
5. Length (2 bytes for character and hexadecimal, 1 byte for other types)—length of data item minus 1
6. Multiplicity–M field (3 bytes)—equals 1 if not present
7. Scale–signed integer–S field (2 bytes)—present only for F-, H-, E-, D-, P-, and Z-type data, and only if scale is nonzero

---

1	2	4	5	10	11	12	13	16	17	72	73	80
X'02'	SYM	Space	No. of bytes of text	Space	Text - packed entries						Deck Id and Seq. Number	
1	3	6	2	4	56						8	

Text

Entry (Complete or end portion)	N Complete entries N >= 1	Entry (Complete or head portion)
Variable size entries		

Entry

Org.	Address	Symbol name	Data Type	Length	Mult. Factor	Scale
1	3	0-8	1	1-2	3	2

---

*Figure 58. SYM record format*



---


## Appendix D. Associated data file output

When you specify the ADATA assembler option, a file containing associated data is produced by the assembler. When you specify the ADATA suboption of the GOFF assembler option, ADATA records are written to the object data set as text records. You can specify both ADATA and GOFF(ADATA) to produce ADATA records in both the associated data file and the object data set. Information about the assembled program can be extracted from either data set and be used by debugging tools or cross reference tools.

The associated data records are subject to change in future releases of High Level Assembler without prior notice. Any utility which processes associated data files should not process any files with architecture levels beyond those the utility has been designed and tested to process.

The ASMADATA macro maps the records in the associated data file, and the generalized object format data set. The syntax and parameter keywords for this macro are shown on page 268.

## Associated data file output



### Default

PRINT=NOGEN,keyword=NO

### NOGEN

Do not print the generated DSECTs in the listing

### GEN

Print the generated DSECTs in the listing



**NO**

Do not generate a DSECT for this record

**YES**

Generate a DSECT for this record

*keywords*

<b>AID</b>	ADATA Identification DSECT (Type X'0001')
<b>AOPT</b>	Options File Information (Type X'000B')
<b>COMPUNIT</b>	ADATA Compilation Unit Start/End DSECT (Type X'0002')
<b>DCDS</b>	DC/DS DSECT (Type X'0034')
<b>DCX</b>	DC Extension DSECT (Type X'0035')
<b>ESD</b>	External Symbol Dictionary (ESD) DSECT (Type X'0020')
<b>JID</b>	Job Identification DSECT (Type X'0000')
<b>MACH</b>	Machine Instruction DSECT (Type X'0036')
<b>MXREF</b>	Macro and Copy Code Source Summary DSECT (Type X'0060')
<b>MXREFX</b>	Macro and Copy Code Cross Reference DSECT (Type X'0062')
<b>OPT</b>	Options DSECT (Type X'0010')
<b>OUTPUT</b>	Output File DSECT (Type X'000A')
<b>RLD</b>	Relocation Dictionary (RLD) DSECT (Type X'0040')
<b>RXREF</b>	Register Cross Reference DSECT (Type X'0045')
<b>SOURCE</b>	Source Analysis DSECT (Type X'0030')
<b>SRCERR</b>	Source Error DSECT (Type X'0032')
<b>STATS</b>	Statistics DSECT (Type X'0090')
<b>SYM</b>	Symbol DSECT (Type X'0042')
<b>USER</b>	User Data Record DSECT (Type X'0070')
<b>USING</b>	Using Map DSECT (Type X'0080')
<b>XREF</b>	Symbol Cross Reference DSECT (Type X'0044')

---

## Record types

The file contains records classified into different record types. Each type of record provides information about the assembler language program being assembled. Each record consists of two parts:

- A 12-byte header section, which has the same structure for all record types.
- A variable-length data section, which varies by record type.

The header section contains, among other items, the record code which identifies the type of record.

The record types, and their contents, written to the associated data file are:

**Job Identification X'0000'**

Provides information about the assembly job, the host system environment, and the names of the primary input data sets.

## Record types

### **ADATA Identification X'0001'**

Provides a precise time stamp, and a description of the character set used for character data in the file.

The time stamp is represented as Universal Time (UT) with the low-order bit representing 1 microsecond.

### **ADATA Compilation Unit Start/End X'0002'**

Indicates where the associated data records for each assembly unit begin and end. The START record is written to the associated data file at the beginning of each assembly. The END record is written to the associated data file at the end of each assembly. The END record contains a count of the total number of records written to the associated data file.

When there are multiple assembler programs in the input file, there is a START and END record for each program assembled.

### **Output File X'000A'**

Provides information about all the assembler output files used for the assembly.

### **Options File X'000B'**

Provides information about the ASMAOPT file (z/OS and CMS) or library member (z/VSE) used for the assembly, if applicable.

### **Options X'0010'**

Describes the assembler options used for the assembly.

### **External Symbol Dictionary X'0020'**

Describes all the control sections, including DSECTs, defined in the program.

### **Source Analysis X'0030'**

Describes a single source line.

There is one Source Analysis record in the file for each source record which would appear in the listing as if PRINT ON,GEN was active. This includes those source records generated by macro instructions, or included by COPY instructions. A Source Analysis record is also produced for TITLE statements. The FOLD assembler option does not cause the source in the Source Analysis record to be converted to uppercase.

The Source Analysis records appear in the sequence they would appear in the listing. Conditional assembly statements might cause the source statements to be skipped or the sequence of the records to be altered.

### **Source Error X'0032'**

Describes errors in source program statements.

All Source Error records follow the Source Analysis record to which they apply.

### **DC/DS X'0034'**

Describes the constant or storage defined by a source program statement that contains a DC, DS, CXD, DXD, CCW, CCW0, or CCW1 instruction.

If a source program statement contains one of the above, then a DC/DS record is written following the Source Analysis record.

If there is an error in the DC, DS, CXD, DXD, CCW, CCW0, or CCW1 instruction, the DC/DS record is not produced.

If the DC statement has a duplication factor greater than 1, and at least one of the operand values has a reference to the current location counter (\*), then a DC extension record (X'0035') is generated.

**DC Extension X'0035'**

This record describes the object text generated by a DC statement when the DC statement has repeating fields. This record is only created if the DC statement has a duplication factor greater than 1 and at least one of the operand values has a reference to the current location counter (\*).

**Machine Instruction X'0036'**

Describes the object code generated for a source program statement.

If a source program statement causes machine instructions to be generated, then a Machine Instruction record is written following the source record. If there is an error in the machine instruction, the Machine Instruction record follows the Source Error record.

**Relocation Dictionary X'0040'**

Describes the relocation dictionary information that is contained in the object module RLD records.

**Symbol X'0042'**

Describes a single symbol defined in the program.

There is one Symbol record for each symbol defined in the program, including literals.

**Symbol and Literal Cross Reference X'0044'**

Describes the references to a single symbol.

All Symbol and Literal Cross Reference records follow the Symbol record to which they apply.

**Register Cross Reference X'0045'**

Describes the references to a single register.

**Macro and Copy Code Source Summary X'0060'**

Describes the source of each macro and copy code member retrieved by the program.

**Macro and Copy Code Cross Reference X'0062'**

Describes the references to a single macro, or member copied by the COPY assembler instruction.

**User Data X'0070'**

Describes the data written by the ADATA assembler instruction.

**Using Map X'0080'**

Describes all USING, DROP, PUSH USING, and POP USING statements in the program.

**Statistics X'0090'**

Describes the statistics about the assembly.

Figure 59 on page 272 shows part of the listing of an assembler program. If this assembler program were assembled with the ADATA option, the records produced in the associated data file would be in the sequence shown below Figure 59.

## Record types

---

Loc	Object Code	Addr1	Addr2	Stmt	Source	Statement	HLASM R6.0	2008/07/11	17.48
		00000	0001E	1	CSECTNAM	CSECT			FIG00010
000000	90EC D00C		0000C	2		STM 14,12,12(13)			FIG00020
	R:F	00000		3		USING CSECTNAM,15			FIG00030
000004	0000 0000		00000	4	A	2,FIELD3			FIG00040
** ASMA044E Undefined symbol - FIELD3									
000008	98EC D00C		0000C	5	LM	14,12,12(13)			FIG00050
00000C	07FE			6	BR	14			FIG00060
				7	DROP	15			FIG00070
				8	COPY	ADATA			FIG00080
00000E				9=FIELD1	DS	CL8			ADA00010
000016				10=FIELD2	DS	CL8			ADA00020
				11	END				FIG00090

---

Figure 59. Sample assembler program for associated data output

Type	Description
X'0002'	ADATA Compilation Unit START record
X'0001'	ADATA Identification record
X'0000'	Job Identification record
X'0010'	Options record
X'0020'	External Symbol Dictionary record for CSECTNAM
X'0030'	Source record for statement 1 CSECTNAM CSECT
X'0030'	Source record for statement 2 STM 14,12,12(13)
X'0036'	Machine Instruction record for STM instruction
X'0030'	Source record for statement 3 USING CSECTNAM,15
X'0030'	Source record for statement 4 A 2,FIELD3
X'0032'	Source Error record for message ASMA044E
X'0036'	Machine Instruction record for A instruction
X'0030'	Source record for statement 5 LM 14,12,12(13)
X'0036'	Machine Instruction record for LM instruction
X'0030'	Source record for statement 6 BR 14
X'0036'	Machine Instruction record for BR instruction
X'0030'	Source record for statement 7 DROP 15
X'0030'	Source record for statement 8 COPY ADATA
X'0030'	Source record for statement 9 (From COPY member ADATA) FIELD1 DS CL8
X'0034'	DC/DS record for FIELD1
X'0030'	Source record for statement 10 (From COPY member ADATA) FIELD2 DS CL8
X'0034'	DC/DS record for FIELD2
X'0030'	Source record for statement 11 END
X'0042'	Symbol record for CSECTNAM
X'0044'	Symbol and Literal Cross Reference record for CSECTNAM
X'0042'	Symbol record for FIELD1
X'0042'	Symbol record for FIELD2
X'0042'	Symbol record for FIELD3
X'0044'	Symbol and Literal Cross Reference record for FIELD3
X'0044'	Symbol and Literal Cross Reference record for FIELD1
X'0044'	Symbol and Literal Cross Reference record for FIELD2
X'0060'	Macro and Copy Code Source Summary record for COPY ADATA

X'0062'	Macro and Copy Code Cross Reference record for COPY ADATA
X'0080'	USING Map record for USING on statement 3
X'0080'	USING Map record for DROP on statement 7
X'0045'	Register Cross Reference records...
:	
:	
X'0045'	...for each register referenced (0–15) <sup>1</sup>
X'0090'	Assembly Statistics record
X'0002'	ADATA Compilation Unit END record
	The count value in this record is 54.

**Notes:**

1. There is one X'0045' record for each of the sixteen registers due to the implicit references by the STM and LM instructions.

**Macro-only assemblies**

The associated data file can also be useful for assemblies that have macro processing only (SYSGENs for example). The printing of the generated assembler source is not printed in the listing, but the information is available in the associated data file. Figure 60 shows part of the listing of an assembler program that only includes a macro instruction. The statements generated by the macro instruction (statements 9 through 11) are not printed on the listing. If this program were assembled with the ADATA option, the records produced in the associated data file would be in the sequence shown below.

---

Loc	Object Code	Addr1	Addr2	Stmnt	Source	Statement	HLASM R6.0	2008/07/11	17.48
				1		print nogen			00001000
				2		macro			00002000
				3	&NAME	testhla &job			00003000
				4		punch '//&job JOB'			00004000
				5		punch '//STEP1 EXEC PGM=ABC'			00005000
				6		punch '//DDNAME1 DD DSN=DSN.&job.,DISP=SHR'			00006000
				7		mend			00007000
				8		TESTHLA TESTJOB			00008000
				12		END			00009000

---

Figure 60. Sample assembler program for macro-only assembly

Type	Description
X'0002'	ADATA Compilation Unit START record
X'0001'	ADATA Identification record
X'0000'	Job Identification record
X'000A'	Output File record
X'0010'	Options record
X'0030'	Source record for statement 1 print nogen
X'0030'	Source record for statement 2 macro
X'0030'	Source record for statement 3 &NAME testhla &job
X'0030'	Source record for statement 4 punch '//&job JOB'
X'0030'	Source record for statement 5 punch '//STEP1 EXEC PGM=ABC'
X'0030'	Source record for statement 6 punch '//DDNAME1 DD DSN=DSN.&job.,DISP=SHR'
X'0030'	Source record for statement 7 mend

## Record types

X'0030'	Source record for statement 8 TESTHLA TESTJOB
X'0030'	Source record for statement 9 punch '//TESTJOB JOB'
X'0030'	Source record for statement 10 punch '//STEP1 EXEC PGM=ABC'
X'0030'	Source record for statement 11 punch '//DDNAME1 DD DSN=DSN.TESTJOB,DISP=SHR'
X'0030'	Source record for statement 12 END
X'0060'	Macro and Copy Code Source Summary record for macro TESTHLA
X'0062'	Macro and Copy Code Cross Reference record for macro TESTHLA
X'0090'	Assembly Statistics record
X'0002'	ADATA Compilation Unit END record The count value in this record is 21.

---

## ADATA record layouts

The formats of the records written to the associated data file are shown in the sections that follow.

In the fields described in each of the record types, a notation based on the assembler language data type is used:

C	indicates EBCDIC data
H	indicates 2-byte binary integer data
F	indicates 4-byte binary integer data
A	indicates 4-byte binary address data
X	indicates hexadecimal (bit) data

No boundary alignments are implied by any data type, and you can change the implied lengths by using a length indicator (*Ln*). All integer data is in *System/370* format; that is bit 0 is always the most significant bit, bit *n* is the least significant bit, and the byte ordering in the records is from most significant to the least significant. The bits within a byte are numbered from left to right starting from 0.

Offsets within each record are calculated from the beginning of the header section.

---

## Common header section

Each ADATA record contains a 12-byte common header section.

All ADATA records at the same architecture level have the same header section which describes: the producing language, the record type, the record architecture level (or version), a continued-record indicator, and, starting at level 2, an edition number.

High Level Assembler Release 5 produces architecture level 3 header records. This level is described in the following sections.

*Table 37. ADATA record—common header section*

Field	Size	Description
Language code	FL1	16 Assembler

Table 37. ADATA record—common header section (continued)

Field	Size	Description
Record type	XL2	<p>The record type, which can be one of the following:</p> <p>X'0000' Job Identification record</p> <p>X'0001' ADATA Identification record</p> <p>X'0002' Compilation Unit Start/End record</p> <p>X'000A' Output File Information record</p> <p>X'000B' Options File Information record</p> <p>X'0010' Options record</p> <p>X'0020' External Symbol Dictionary record</p> <p>X'0030' Source Analysis record</p> <p>X'0032' Source Error record</p> <p>X'0034' DC/DS record</p> <p>X'0035' DC Extension record</p> <p>X'0036' Machine Instruction record</p> <p>X'0040' Relocation Dictionary record</p> <p>X'0042' Symbol record</p> <p>X'0044' Symbol and Literal Cross Reference record</p> <p>X'0045' Register Cross Reference record</p> <p>X'0060' Macro and Copy Code Source Summary record</p> <p>X'0062' Macro and Copy Code Cross Reference record</p> <p>X'0070' User Data record</p> <p>X'0080' USING Map record</p> <p>X'0090' Assembly Statistics record</p>
Associated Data Architecture level	FL1	3
Flag	XL1	<p>.... ...0 Record is not continued</p> <p>.... ...1 Record is continued on the next record</p> <p>.... ..0. Length fields are big-endian (S/390®, RS/6000®)</p> <p>.... ...1. Length fields are little-endian (Intel®)</p> <p>All other values are reserved.</p>

## Common header section

Table 37. ADATA record—common header section (continued)

Field	Size	Description																																										
Edition Number	FL1	<p>The edition number of this record type.</p> <p>The following list of edition number values can be used to determine the format of each ADATA record. The listed edition number value (or higher) indicates that the record is in the new restructured High Level Assembler Release 5 format.</p> <table><tr><td>1</td><td>Job Identification record</td></tr><tr><td>0</td><td>ADATA Identification record</td></tr><tr><td>0</td><td>Compilation Unit Start/End record</td></tr><tr><td>1</td><td>Output File Information record</td></tr><tr><td>1</td><td>Options File Information record</td></tr><tr><td>3</td><td>Options record</td></tr><tr><td>1</td><td>External Symbol Dictionary record</td></tr><tr><td>1</td><td>Source Analysis record</td></tr><tr><td>1</td><td>Source Error record</td></tr><tr><td>1</td><td>DC/DS record</td></tr><tr><td>1</td><td>DC Extension record</td></tr><tr><td>1</td><td>Machine Instruction record</td></tr><tr><td>1</td><td>Relocation Dictionary record</td></tr><tr><td>1</td><td>Symbol record</td></tr><tr><td>1</td><td>Symbol and Literal Cross Reference record</td></tr><tr><td>1</td><td>Register Cross Reference record</td></tr><tr><td>1</td><td>Macro and Copy Code Source Summary record</td></tr><tr><td>1</td><td>Macro and Copy Code Cross Reference record</td></tr><tr><td>1</td><td>User Data record</td></tr><tr><td>1</td><td>USING Map record</td></tr><tr><td>2</td><td>Assembly Statistics record</td></tr></table>	1	Job Identification record	0	ADATA Identification record	0	Compilation Unit Start/End record	1	Output File Information record	1	Options File Information record	3	Options record	1	External Symbol Dictionary record	1	Source Analysis record	1	Source Error record	1	DC/DS record	1	DC Extension record	1	Machine Instruction record	1	Relocation Dictionary record	1	Symbol record	1	Symbol and Literal Cross Reference record	1	Register Cross Reference record	1	Macro and Copy Code Source Summary record	1	Macro and Copy Code Cross Reference record	1	User Data record	1	USING Map record	2	Assembly Statistics record
1	Job Identification record																																											
0	ADATA Identification record																																											
0	Compilation Unit Start/End record																																											
1	Output File Information record																																											
1	Options File Information record																																											
3	Options record																																											
1	External Symbol Dictionary record																																											
1	Source Analysis record																																											
1	Source Error record																																											
1	DC/DS record																																											
1	DC Extension record																																											
1	Machine Instruction record																																											
1	Relocation Dictionary record																																											
1	Symbol record																																											
1	Symbol and Literal Cross Reference record																																											
1	Register Cross Reference record																																											
1	Macro and Copy Code Source Summary record																																											
1	Macro and Copy Code Cross Reference record																																											
1	User Data record																																											
1	USING Map record																																											
2	Assembly Statistics record																																											
Reserved	XL4																																											
Associated Data Field length	HL2	The length, in bytes, of the data following the header																																										

### Note:

1. The mapping of the 12-byte header does not include the area used for the variable-length, record-descriptor word required by the access method.
2. The BATCH option, when used in conjunction with the ADATA option, produces a group of records for each assembly. Each group of records is delimited by the ADATA Compilation Start/End records.
3. All undefined and unused values are reserved.
4. If Flag indicates that the record is continued, the continue record follows the current record. The continue record includes the Common Header Section and has the same Record Type. If the continue record is continued then Flag is set with the continuation indicator.

## Job Identification Record—X'0000'

Field	Size	Description
Date	CL8	The date of the assembly in the format YYYYMMDD
Time	CL4	The time of the assembly in the format HHMM
Product number	CL8	The product number of the assembler that produced the associated data file
Product version	CL8	The version number of the assembler that produced the associated data file, in the form V.R.M and padded to the right with spaces. For example, C'1.5.0 '.



Field	Size	Description
Product level	HL2	A monotonically increasing numeric value which identifies the current version and release of the assembler
PTF level	CL8	The PTF level number of the assembler that produced the associated data file
System ID	CL24	The system identification of the operating system on which the assembly was run. The value of the field is set to the value of the system variable &SYSTEM_ID.
Jobname	CL8	The jobname of the assembly job
Stepname	CL8	The z/OS stepname of the assembly step
Procstep	CL8	The z/OS procedure step name of the assembly procedure step
Number of input files (SYSIN)	FL4	The number of input files in this record.  The groups of eleven input-file fields below occur <i>n</i> times depending on the value in this field.
Offset of first input-file	FL4	The offset from the beginning of this record to the first group of input-file fields. A value of binary zeros indicates that there are no input files.
<b>Start of input-file information groups, one group per file.</b> <b>The ellipses (...) indicate the fields are grouped.</b>		
...Offset of next input-file	FL4	The offset from the beginning of this record to the next group of input-file fields. A value of binary zeros indicates that there are no more input files.
...Input file number	FL4	The assigned sequence number of the input file
...Input file name offset	FL4	The offset from the beginning of this record to the input file name
...Input file name length	FL4	The length of the input file name
...Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number
...Volume serial number length	FL4	The length of the volume serial number
...Member name offset	FL4	The offset from the beginning of this record to the member name. If no member name is applicable, this field will contain binary zeros.
...Member name length	FL4	The length of the member name. If no member name is applicable, this field will contain binary zeros.
...Input file name	CL(n)	The name of the input file for the assembly
...Volume serial number	CL(n)	The volume serial number of the (first) volume on which the input file resides
...Member name	CL(n)	Where applicable, the name of the member in the input file
<b>End of input-file information group.</b>		

## Job Identification Record—X'0000'

Field	Size	Description
<b>Note:</b>		
1. If a SOURCE user exit has been specified for the assembly, and the SOURCE user exit has opened the input file, the input file details are those returned by the user exit.		
2. Where the number of input files would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of input files (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent input files. The count of the number of input files is a count for the current record.		
Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.		

## ADATA Identification Record—X'0001'

Field	Size	Description
Time (binary)	XL8	Universal Time (UT) with the low-order bit representing 1 microsecond.  This time may be used as a time-zone-independent time stamp.
CCSID	XL2	Coded Character Set Identifier for any character data within the file

## ADATA Compilation Unit Start/End Record—X'0002'

Field	Size	Description
Indicator	XL2	Start/End Indicator
		X'0000' Start of a group of compilation-unit-related ADATA records
		X'0001' End of a group of compilation-unit-related ADATA records
	XL2	All other values are reserved.
		Reserved
Record Count	FL4	On an ADATA Compilation Unit End record, a count of all the ADATA records for this compilation unit. (On an ADATA Compilation Unit Start record, this field should be zero, unless the producing translator has foreknowledge of the exact number of records to be written, in which case it must be identical to the count in the Compilation Unit End record. Otherwise, it may be ignored by any consumer of the ADATA stream.)  In High Level Assembler, the record count in the ADATA Compilation Unit Start record is always zero.

## Output File Information Record—X'000A'

The Output File Information record provides data about the files produced by the translator.

This architecture level provides for five such output files:

1. The object data set produced when you specify the OBJECT or GOFF (z/OS and CMS) option
2. The object data set produced when you specify the DECK option
3. The listing file produced when you specify the LIST option
4. The terminal messages file produced when you specify the TERM option
5. The SYSADATA file produced when you specify the ADATA option

Field	Size	Description
Number of primary object-file (OBJECT) output files	FL4	The number of primary object-files in this record.  The groups of eleven primary object-file fields below occur <i>n</i> times depending on the value in this field. (This number is normally 1.)
Offset of first primary object-file	FL4	The offset from the beginning of this record to the first group of primary object-file fields. A value of binary zeros indicates that there are no primary object-files.
Number of secondary object-file (PUNCH) output files	FL4	The number of secondary (punch) object-files in this record.  The groups of eleven secondary object-file fields below occur <i>n</i> times depending on the value in this field. (This number is normally 1.)
Offset of first secondary object-file	FL4	The offset from the beginning of this record to the first group of secondary object-file fields. A value of binary zeros indicates that there are no secondary object-files.
Number of listing (PRINT) output files	FL4	The number of listing (print) files in this record.  The groups of eleven listing-file fields below occur <i>n</i> times depending on the value in this field. (This number is normally 1.)
Offset of first listing-file	FL4	The offset from the beginning of this record to the first group of listing-file fields. A value of binary zeros indicates that there are no listing files.
Number of terminal (TERM) output files	FL4	The number of terminal files in this record.  The groups of eleven terminal-file fields below occur <i>n</i> times depending on the value in this field. (This number is normally 1.)
Offset of first terminal-file	FL4	The offset from the beginning of this record to the first group of terminal-file fields. A value of binary zeros indicates that there are no terminal files.
Number of associated-data (ADATA) output files	FL4	The number of associated-data files in this record.  The groups of eleven associated-data output-file fields below occur <i>n</i> times depending on the value in this field. (This number is normally 1.)
Offset of first associated-data file	FL4	The offset from the beginning of this record to the first group of associated-data-file fields. A value of binary zeros indicates that there are no associated-data files.

## Output File Information Record—X'000A'

Field	Size	Description
<b>Start of primary object-file information groups, one group per file.</b> <b>The ellipses (...) indicate the fields are grouped.</b>		
...Offset of next primary object-file	FL4	The offset from the beginning of this record to the next group of primary object-file fields. A value of binary zeros indicates that there are no more primary object-files.
...Primary object-file file number	FL4	The assigned sequence number of the primary object-file
...Primary object-file name offset	FL4	The offset from the beginning of this record to the output file name for the primary object-file
...Primary object-file name length	FL4	The length of the output file name for the primary object-file
...Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number for the primary object-file
...Volume serial number length	FL4	The length of the volume serial number for the primary object-file
...Member name offset	FL4	The offset from the beginning of this record to the member name in the primary object-file. If no member name is applicable, this field will contain binary zeros.
...Member name length	FL4	The length of the member name in the primary object-file. If no member name is applicable, this field will contain binary zeros.
...Primary object-file name	CL(n)	The name of the primary object-file for the assembly
...Volume serial number	CL(n)	The volume serial number of the volume on which the primary object-file resides
...Member name	CL(n)	Where applicable, the name of the member in the primary object-file.
<b>End of primary object-file information group.</b>		
<b>Start of secondary object-file information groups, one group per file.</b> <b>The ellipses (...) indicate the fields are grouped.</b>		
...Offset of next secondary object-file	FL4	The offset from the beginning of this record to the next group of secondary object-file fields. A value of binary zeros indicates that there are no more secondary object-files.
...Secondary object- file file number	FL4	The assigned sequence number of the secondary object-file
...Secondary object-file name offset	FL4	The offset from the beginning of this record to the output file name for the secondary object-file
...Secondary object-file name length	FL4	The length of the output file name for the secondary object-file
...Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number for the secondary object-file
...Volume serial number length	FL4	The length of the volume serial number for the secondary object-file
...Member name offset	FL4	The offset from the beginning of this record to the member name in the secondary object-file. If no member name is applicable, this field will contain binary zeros.

## Output File Information Record—X'000A'

Field	Size	Description
...Member name length	FL4	The length of the member name in the secondary object-file. If no member name is applicable, this field will contain binary zeros.
...Secondary object- file name	CL(n)	The name of the secondary object-file for the assembly
...Volume serial number	CL(n)	The volume serial number of the volume on which the secondary object-file resides
...Member name	CL(n)	Where applicable, the name of the member in the secondary object-file.
<b>End of secondary object-file information group.</b>		
<b>Start of listing-file information groups, one group per file.</b> <b>The ellipses (...) indicate the fields are grouped.</b>		
...Offset of next listing-file	FL4	The offset from the beginning of this record to the next group of listing-file fields. A value of binary zeros indicates that there are no more listing files.
...Listing-file file number	FL4	The assigned sequence number of the listing file
...Listing-file name offset	FL4	The offset from the beginning of this record to the output file name for the listing file
...Listing-file name length	FL4	The length of the output file name for the listing file
...Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number for the listing file
...Volume serial number length	FL4	The length of the volume serial number for the listing file
...Member name offset	FL4	The offset from the beginning of this record to the member name in the listing file. If no member name is applicable, this field will contain binary zeros.
...Member name length	FL4	The length of the member name in the listing file. If no member name is applicable, this field will contain binary zeros.
...Listing-file name	CL(n)	The name of the listing file for the assembly
...Volume serial number	CL(n)	The volume serial number of the volume on which the listing file resides
...Member name	CL(n)	Where applicable, the name of the member in the listing file.
<b>End of listing-file information group.</b>		
<b>Start of terminal-file information groups, one group per file.</b> <b>The ellipses (...) indicate the fields are grouped.</b>		
...Offset of next terminal-file	FL4	The offset from the beginning of this record to the next group of terminal-file fields. A value of binary zeros indicates that there are no more terminal files.
...Terminal-file file number	FL4	The assigned sequence number of the terminal file
...Terminal-file name offset	FL4	The offset from the beginning of this record to the output file name for the terminal file
...Terminal-file name length	FL4	The length of the output file name for the terminal file

## Output File Information Record—X'000A'

Field	Size	Description
...Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number for the terminal file
...Volume serial number length	FL4	The length of the volume serial number for the terminal file
...Member name offset	FL4	The offset from the beginning of this record to the member name in the terminal file. If no member name is applicable, this field will contain binary zeros.
...Member name length	FL4	The length of the member name in the terminal file. If no member name is applicable, this field will contain binary zeros.
...Terminal-file name	CL(n)	The name of the terminal file for the assembly
...Volume serial number	CL(n)	The volume serial number of the volume on which the terminal file resides
...Member name	CL(n)	Where applicable, the name of the member in the terminal file.
<b>End of terminal-file information group.</b>		
<b>Start of associated-data-file information groups, one group per file.</b> <b>The ellipses (...) indicate the fields are grouped.</b>		
...Offset of next associated-data file	FL4	The offset from the beginning of this record to the next group of associated-data-file fields. A value of binary zeros indicates that there are no more associated-data files.
...Associated-data-file file number	FL4	The assigned sequence number of the associated-data file
...Associated-data file name offset	FL4	The offset from the beginning of this record to the output file name for the associated-data file
...Associated-data file name length	FL4	The length of the output file name for the associated-data file
...Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number for the associated-data file
...Volume serial number length	FL4	The length of the volume serial number for the associated-data file
...Member name offset	FL4	The offset from the beginning of this record to the member name in the associated-data file. If no member name is applicable, this field will contain binary zeros.
...Member name length	FL4	The length of the member name in the associated-data file. If no member name is applicable, this field will contain binary zeros.
...Associated-data file name	CL(n)	The name of the associated-data file for the assembly
...Volume serial number	CL(n)	The volume serial number of the volume on which the associated-data file resides
...Member name	CL(n)	Where applicable, the name of the member in the associated-data file
<b>End of associated-data-file information group.</b>		

## Output File Information Record—X'000A'

Field	Size	Description
<b>Note:</b>		
Where the number of output files would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of output files (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent output files. The count of the number of output files is a count for the current record.		
Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.		

## Options File Information—X'000B'

The Options File Information record provides data about any option files passed to the assembler; using an external file (z/OS and CMS) with the DDname ASMAOPT or library member (z/VSE) with the name and type ASMAOPT.USER.

Field	Size	Description
Number of option (ASMAOPT) input files	FL4	The number of option files in this record.  The groups of eleven option-file fields below occur <i>n</i> times depending on the value in this field.
Offset of option file	FL4	The offset from the beginning of this record to the first group of option-file fields. A value of binary zeros indicates that there are no option files.
<b>Start of option-file information groups, one group per file.</b> <b>The ellipses (...) indicate the fields are grouped.</b>		
...Offset of next option file	FL4	The offset from the beginning of this record to the next group of option-file fields. A value of binary zeros indicates that there are no more option files.
...Option file number	FL4	The assigned sequence number of the option file
...Option file name offset	FL4	The offset from the beginning of this record to the option file name
...Option file name length	FL4	The length of the option file name
...Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number
...Volume serial number length	FL4	The length of the volume serial number
...Member name offset	FL4	The offset from the beginning of this record to the member name. If no member name is applicable, this field will contain binary zeros.
...Member name length	FL4	The length of the member name. If no member name is applicable, this field will contain binary zeros.
...Option file name	CL(n)	The name of the option file for the assembly
...Volume serial number	CL(n)	The volume serial number of the (first) volume on which the option file resides
...Member name	CL(n)	Where applicable, the name of the member in the option file
<b>End of option-file information group.</b>		

## Options File Information—X'000B'

Field	Size	Description
<b>Note:</b>		
Where the number of option files would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of option files (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent option files. The count of the number of option files is a count for the current record.		
Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.		

## Options record—X'0010'

This record indicates which assembler options were used for the assembly, and the values passed as suboptions. For example, if the PROFILE option was specified, bit 7 in option byte 8 would be 1, and the PROFILE value field would contain the profile member name.

The layout of the first 12 option bytes matches that of the assembler's option bytes in the ASMADOPT module.

Field	Size	Description
Option Byte 1	XL1	<b>1...</b> .... Bit 1 = DECK, Bit 0 = NODECK
		<b>.1.</b> .... Bit 1 = OBJECT, Bit 0 = NOOBJECT
		<b>..1.</b> .... Bit 1 = LIST, Bit 0 = NOLIST
		<b>...1</b> .... Bit 1 = XREF, Bit 0 = NOXREF
		<b>.... 1..</b> Bit 1 = RENT, Bit 0 = NORENT
		<b>.... .1..</b> Bit 1 = TEST, Bit 0 = NOTEST
		<b>.... ..1.</b> Bit 1 = BATCH, Bit 0 = NOBATCH
		<b>.... ...1</b> Bit 1 = ALIGN, Bit 0 = NOALIGN
Option Byte 2	XL1	<b>1...</b> .... Bit 1 = ESD, Bit 0 = NOESD
		<b>.1.</b> .... Bit 1 = RLD, Bit 0 = NORLD
		<b>..1.</b> .... Bit 1 = XREF(SHORT), Bit 0 = not XREF(SHORT)
		<b>...1</b> .... Bit 1 = TRACE specified, Bit 0 = not specified
		<b>.... 1..</b> Bit 1 = XREF(FULL), Bit 0 = not XREF(FULL)
		<b>.... .1..</b> Bit 1 = SIZE(MAX..,ABOVE), Bit 0 = not SIZE(MAX..,ABOVE)
		<b>.... ..1.</b> Bit 1 = XREF(UNREFS), Bit 0 = not XREF(UNREFS)
		<b>.... ...1</b> Bit 1 = RXREF, Bit 0 = NORXREF
Option Byte 3	XL1	<b>1...</b> .... Bit 1 = TERM, Bit 0 = NOTERM
		<b>.1.</b> .... Bit 1 = TERM(NARROW), Bit 0 = not TERM(NARROW)
		<b>..1.</b> .... Bit 1 = DBCS, Bit 0 = NODBCS
		<b>...1</b> .... Bit 1 = DXREF, Bit 0 = NODXREF
		<b>.... 1..</b> Bit 1 = FOLD, Bit 0 = NOFOLD
		<b>.... .1..</b> Bit 1 = SIZE specified, Bit 0 = not specified
		<b>.... ..1.</b> Bit 1 = FLAG(PUSH), Bit 0 = FLAG(NOPUSH)
		<b>.... ...1</b> Bit 1 = THREAD, Bit 0 = NOTHREAD



Field	Size	Description
Option Byte 4	XL1	<b>1...</b> .... Bit 1 = PCONTROL(ON), Bit 0 = not PCONTROL(ON)
		<b>.1..</b> .... Bit 1 = PCONTROL(GEN), Bit 0 = not PCONTROL(GEN)
		<b>..1.</b> .... Bit 1 = PCONTROL(DATA), Bit 0 = not PCONTROL(DATA)
		<b>...1</b> .... Bit 1 = PCONTROL(UHEAD), Bit 0 = not PCONTROL(UHEAD)
		<b>.... 1..</b> Bit 1 = PCONTROL(MSOURCE), Bit 0 = not PCONTROL(MSOURCE)
		<b>.... .1..</b> Bit 1 = SECTALGN specified, Bit 0 = not specified
		<b>.... ..1.</b> Reserved
		<b>.... ...1</b> Reserved
Option Byte 5	XL1	<b>1...</b> .... Bit 1 = ASA, Bit 0 = NOASA (z/OS and CMS)
		<b>.1..</b> .... Bit 1 = USING(WARN(m)), Bit 0 = USING(NOWARN)
		<b>..1.</b> .... Bit 1 = USING(LIMIT(nnnn)), Bit 0 = USING(NOLIMIT)
		<b>...1</b> .... Bit 1 = USING(MAP), Bit 0 = USING(NOMAP)
		<b>.... 1..</b> Bit 1 = INEXIT, Bit 0 = NOINEXIT
		<b>.... .1..</b> Bit 1 = LIBEXIT, Bit 0 = NOLIBEXIT
		<b>.... ..1.</b> Bit 1 = PRTEXTIT, Bit 0 = NOPRTEXTIT
		<b>.... ...1</b> Bit 1 = OBJEXIT, Bit 0 = NOOBJEXIT
Option Byte 6	XL1	<b>1...</b> .... Bit 1 = SYSPARM specified, Bit 0 = not specified
		<b>.1..</b> .... Bit 1 = FLAG specified, Bit 0 = not specified
		<b>..1.</b> .... Bit 1 = LANGUAGE specified, Bit 0 = not specified
		<b>...1</b> .... Bit 1 = LINECOUNT specified, Bit 0 = not specified
		<b>.... 1..</b> Bit 1 = OPTABLE/MACHINE specified, Bit 0 = not specified
		<b>.... .1..</b> Bit 1 = ADATA, Bit 0 = NOADATA
		<b>.... ..1.</b> Bit 1 = ADEXIT, Bit 0 = NOADEXIT
		<b>.... ...1</b> Bit 1 = TRMEXIT, Bit 0 = NOTRMEXIT
Option Byte 7	XL1	<b>1...</b> .... Bit 1 = LIST(121), Bit 0 = not LIST(121) (z/OS and CMS)
		<b>.1..</b> .... Bit 1 = LIST(133), Bit 0 = not LIST(133) (z/OS and CMS)
		<b>..1.</b> .... Bit 1 = LIST(MAX), Bit 0 = not LIST(MAX) (z/OS and CMS)
		<b>...1</b> .... Reserved
		<b>.... 1..</b> Reserved
		<b>.... .1..</b> Reserved
		<b>.... ..1.</b> Reserved
		<b>.... ...1</b> Reserved

## Options record—X'0010'

Field	Size	Description
Option Byte 8	XL1	<b>1...</b> .... Bit 1 = MXREF, Bit 0 = NOMXREF
		<b>.1..</b> .... Bit 1 = MXREF(FULL), Bit 0 = not MXREF(FULL)
		<b>..1.</b> .... Bit 1 = MXREF(SOURCE), Bit 0 = not MXREF(SOURCE)
		<b>...1</b> .... Bit 1 = MXREF(XREF), Bit 0 = not MXREF(XREF)
		<b>.... 1...</b> Bit 1 = TRANSLATE specified, Bit 0 = NOTTRANSLATE
		<b>.... .1..</b> Bit 1 = GOFF, Bit 0 = NOGOFF (z/OS and CMS)
		<b>.... ..1.</b> Bit 1 = GOFF(ADATA), Bit 0 = GOFF(NOADATA) (z/OS and CMS)
		<b>.... ...1</b> Bit 1 = PROFILE specified, Bit 0 = NOPROFILE
Option Byte 9	XL1	<b>1...</b> .... Bit 1 = FLAG(RECORD), Bit 0 = FLAG(NORECORD)
		<b>.1..</b> .... Bit 1 = PCONTROL(MCALL), Bit 0 = not PCONTROL(MCALL)
		<b>..1.</b> .... Bit 1 = PCONTROL(OFF), Bit 0 = not PCONTROL(OFF)
		<b>...1</b> .... Bit 1 = PCONTROL(NODATA), Bit 0 = not PCONTROL(NODATA)
		<b>.... 1...</b> Bit 1 = PCONTROL(NOGEN), Bit 0 = not PCONTROL(NOGEN)
		<b>.... .1..</b> Bit 1 = PCONTROL(NOUHEAD), Bit 0 = not PCONTROL(NOUHEAD)
		<b>.... ..1.</b> Bit 1 = PCONTROL(NOMSOURCE), Bit 0 = not PCONTROL(NOMSOURCE)
		<b>.... ...1</b> Bit 1 = PCONTROL(NOMCALL), Bit 0 = not PCONTROL(NOMCALL)
Option Byte 10	XL1	<b>1...</b> .... Reserved
		<b>.1..</b> .... Reserved
		<b>..1.</b> .... Reserved
		<b>...1</b> .... Bit 1 = WORKFILE, Bit 0 = not specified
		<b>.... 1...</b> Bit 1 = OPTABLE/MACHINE(LIST), Bit 0 = (NOLIST)
		<b>.... .1..</b> Bit 1 = CODEPAGE specified, Bit 0 = not specified
		<b>.... ..1.</b> Bit 1 = Option errors encountered, Bit 0 = no errors encountered
		<b>.... ...1</b> Bit 1 = INFO, Bit 0 = NOINFO

Field	Size	Description
Option Byte 11	XL1	<b>1...</b> .... Bit 1 = FLAG(EXLITW), Bit 0 = FLAG(NOEXLITW)
		<b>.1.</b> .... Bit 1 = TYPECHECK(MAGNITUDE), Bit 0 = TYPECHECK(NOMAGNITUDE)
		<b>..1.</b> .... Reserved
		<b>...1</b> .... Bit 1 = TYPECHECK(REGISTER), Bit 0 = TYPECHECK(NOREGISTER)
		<b>.... 1...</b> Bit 1 = COMPAT(CASE), Bit 0 = COMPAT(NOCASE)
		<b>.... .1.</b> Bit 1 = COMPAT(SYSLIST), Bit 0 = COMPAT(NOSYSLIST)
		<b>.... ..1.</b> Bit 1 = COMPAT(LITTYPE), Bit 0 = COMPAT(NOLITTYPE)
		<b>.... ...1</b> Bit 1 = COMPAT(MACROCASE), Bit 0 = COMPAT(NOMACROCASE)
Option Byte 12	XL1	<b>1...</b> .... Bit 1 = FLAG(USING0), Bit 0 = (NOUSING0)
		<b>.1.</b> .... Bit 1 = LIBMAC, Bit 0 = NOLIBMAC
		<b>..1.</b> .... Bit 1 = RA2, Bit 0 = NORA2
		<b>...1</b> .... Bit 1 = FLAG(ALIGN), Bit 0 = FLAG(NOALIGN)
		<b>.... 1...</b> Bit 1 = FLAG(CONT), Bit 0 = FLAG(NOCONT)
		<b>.... .1.</b> Bit 1 = FLAG(SUBSTR), Bit 0 = FLAG(NOSUBSTR)
		<b>.... ..1.</b> Bit 1 = FLAG(IMPLEN), Bit 0 = FLAG(NOIMPLEN)
		<b>.... ...1</b> Bit 1 = FLAG(PAGE0), Bit 0 = FLAG(NOPAGE0)
Option Byte 13	XL1	<b>1...</b> .... Bit 1 = SUPRWARN, Bit 0 = NOSUPRWARN
		<b>.1.</b> .... Reserved
		<b>..1.</b> .... Reserved
		<b>...1</b> .... Reserved
		<b>.... 1...</b> Reserved
		<b>.... .1.</b> Reserved
		<b>.... ..1.</b> Reserved
		<b>.... ...1</b> Reserved
Option Byte 14	XL1	<b>1...</b> .... Reserved
		<b>.1.</b> .... Reserved
		<b>..1.</b> .... Reserved
		<b>...1</b> .... Reserved
		<b>.... 1...</b> Reserved
		<b>.... .1.</b> Reserved
		<b>.... ..1.</b> Reserved
		<b>.... ...1</b> Reserved
	XL4	Reserved

## Options record—X'0010'

Field	Size	Description
Extra Byte 1	XL1	<b>1... ..</b> Bit 1 = COMPAT, Bit 0 = NOCOMPAT <b>.1... ..</b> Bit 1 = EXIT, Bit 0 = NOEXIT <b>..1... ..</b> Bit 1 = PCONTROL, Bit 0 = NOPCONTROL <b>...1... ..</b> Bit 1 = PESTOP, Bit 0 = NOPESTOP <b>.... 1...</b> Bit 1 = SUBLIB(DF), Bit 0 = SUBLIB(AE) (z/VSE) <b>.... .1..</b> Reserved <b>.... ..1.</b> Reserved <b>.... ...1</b> Reserved
	XL4	Reserved
CODEPAGE value	CL4	Value from CODEPAGE(xxxx) option in effect for the assembly.
FLAG value	FL1	Value from FLAG(n) option in effect for the assembly. Zero if not provided.
LANGUAGE value	CL3	Value from LANGUAGE(xxx) option in effect for the assembly.
LINECOUNT value	HL2	Value from LINECOUNT(n) option in effect for the assembly.
OPTABLE	CL3	Value from OPTABLE(xxx) option in effect for the assembly.
PROFILE value	CL8	Value from PROFILE(xxxxxxxx) option in effect for the assembly. Blank if not provided.
SECTALGN value	FL4	Value from SECTALGN(n) option in effect for the assembly.
TRANSLATE value	CL2	Value from TRANSLATE(xx) option in effect for the assembly. Blank if not provided.
USING(LIMIT) value	HL2	Value from USING(LIMIT(n)) option in effect for the assembly. Zero if not provided.
USING(WARN) value	FL1	Value from USING(WARN(n)) option in effect for the assembly. Zero if not provided.
	XL32	Reserved
PARM offset	FL4	Offset from the beginning of this record to the PARM string supplied
PARM length	FL4	Length of the PARM string supplied
SYSPARM offset	FL4	Offset from the beginning of this record to the SYSPARM string supplied
SYSPARM length	FL4	Length of the SYSPARM string supplied
Input exit name offset	FL4	Offset from the beginning of this record to the INEXIT program name
Input exit name length	FL4	Length of the INEXIT program name
Input exit string offset	FL4	Offset from the beginning of this record to the string supplied to INEXIT
Input exit string length	FL4	Length of string supplied to INEXIT
Library exit name offset	FL4	Offset from the beginning of this record to the LIBEXIT program name
Library exit name length	FL4	Length of the LIBEXIT program name

Field	Size	Description
Library exit string offset	FL4	Offset from the beginning of this record to the string supplied to LIBEXIT
Library exit string length	FL4	Length of string supplied to LIBEXIT
Print exit name offset	FL4	Offset from the beginning of this record to the PRTEXT program name
Print exit name length	FL4	Length of the PRTEXT program name
Print exit string offset	FL4	Offset from the beginning of this record to the string supplied to PRTEXT
Print exit string length	FL4	Length of string supplied to PRTEXT
Object exit name offset	FL4	Offset from the beginning of this record to the OBJEXIT program name
Object exit name length	FL4	Length of the OBJEXIT program name
Object exit string offset	FL4	Offset from the beginning of this record to the string supplied to OBJEXIT
Object exit string length	FL4	Length of string supplied to OBJEXIT
ADATA exit name offset	FL4	Offset from the beginning of this record to the ADEXIT program name
ADATA exit name length	FL4	Length of the ADEXIT program name
ADATA exit string offset	FL4	Offset from the beginning of this record to the string supplied to ADEXIT
ADATA exit string length	FL4	Length of string supplied to ADEXIT
TERM exit name offset	FL4	Offset from the beginning of this record to the TRMEXIT program name
TERM exit name length	FL4	Length of the TRMEXIT program name
TERM exit string offset	FL4	Offset from the beginning of this record to the string supplied to TRMEXIT
TERM exit string length	FL4	Length of string supplied to TRMEXIT
PARM string	CL(n)	Field to contain the invocation option string that is being used for the assembly
SYSARM string	CL(n)	Field to contain the SYSARM string that is being used for the assembly
Input exit name	CL(n)	INEXIT program name
Input exit string	CL(n)	Field to contain the string to be passed to the INEXIT program
Library exit name	CL(n)	LIBEXIT program name
Library exit string	CL(n)	Field to contain the string to be passed to the LIBEXIT program
Print exit name	CL(n)	PRTEXT program name
Print exit string	CL(n)	Field to contain the string to be passed to the PRTEXT program
Object exit name	CL(n)	OBJEXIT program name
Object exit string	CL(n)	Field to contain the string to be passed to the OBJEXIT program
ADATA exit name	CL(n)	ADEXIT program name
ADATA exit string	CL(n)	Field to contain the string to be passed to the ADEXIT program

## Options record—X'0010'

Field	Size	Description
TERM exit name	CL(n)	TRMEXIT program name
TERM exit string	CL(n)	Field to contain the string to be passed to the TRMEXIT program

## External Symbol Dictionary Record—X'0020'

Field	Size	Description
Record Type	XL1	X'00' Section Definition (CSECT) SD X'01' Label Definition (entry point) LD X'02' External Reference ER X'03' Element Definition (class) ED X'04' Private Code Section PC X'05' Common Section CM X'06' External Dummy Section XD X'07' Part Reference PR X'0A' Weak External Reference WX X'FF' Dummy Section (DSECT) (no type designator)
Flags	XL1	Flags or Alignment  For SD-, PC- and CM-type entries, it contains the AMODE/RMODE flags. For LD-, ER- and WX-type entries, it is space-filled. For XD-type entries, it indicates the number of bytes for alignment less one. xx.. .... Reserved ..r. .... RMODE 64 if 1, otherwise use the R bit ...a .... AMODE 64 if 1, otherwise use the AA bits .... 1... Read-Only Control Section (RSECT) .... .R.. RMODE: 0=RMODE(24), 1=RMODE(ANY) .... ..AA AMODE: 00,01=AMODE(24), 10=AMODE(31), 11=AMODE(ANY)
	XL2	Reserved
ESDID	FL4	External Symbol Dictionary ID (ESDID) or zero
	AL4	Reserved
Address or Alignment	AL4	The section or symbol address, or section alignment.  For SD-, LD- and ED-type entries, it contains the address of the symbol. For PC- and CM-type entries, it indicates the beginning address of the control section. For XD-type entries, it indicates the number of bytes for alignment less one.
	FL4	Reserved
Section Length	FL4	The length of the section
Owner ID	FL4	ESDID of the SD or ED in which this symbol was defined
	XL8	Reserved
External Name offset	FL4	The offset from the beginning of this record to the external name. A value of binary zeros indicates that there is no external name.

## External Symbol Dictionary Record—X'0020'

Field	Size	Description
External Name length	FL4	Number of characters in the external name (zero if private code, unnamed common or unnamed DSECT)
Alias Name offset	FL4	The offset from the beginning of this record to the alias name. A value of binary zeros indicates that there is no alias name.
Alias Name length	FL4	Number of characters in the alias name (zero if no alias)
External name	CL(n)	The external name
Alias Section name	CL(n)	The alias name for the section

## Source Analysis Record—X'0030'

Field	Size	Description
ESDID	FL4	The ESDID for the source record.
Statement number	FL4	The statement number of the source record.
Input record number	FL4	<p>The input source record number within the current input file.</p> <p>If the source line is macro-generated (that is, the input record origin value is X'02'), this field contains binary zero.</p> <p>This field contains the value returned by the exit if the source record is provided by an exit.</p>
Parent record number	FL4	<p>The parent source record number.</p> <p>If the source record was included by a COPY statement or generated by a macro instruction, the Parent input number is the record number of the COPY statement or macro instruction.</p> <p>This field contains the value returned by the input or library exits if the source record is provided by either of these exits.</p>
Input assigned file number	FL4	<p>The input file's assigned sequence number. (Refer to the input file <i>n</i> in the Job Identification record if the Input record origin is X'01', or the Library Record - X'0060' with Concatenation number <i>n</i> otherwise).</p> <p>This field is set to zero if an exit provides the source record.</p>
Parent assigned file number	FL4	<p>The parent file's assigned sequence number. (Refer to the Input file <i>n</i> in the Job Identification record if the Parent record origin is X'01', or the Library Record - X'0060' with Concatenation number <i>n</i> otherwise).</p> <p>This field is set to zero if an exit provides the source record.</p>
Location Counter	FL4	The current location counter for the source record.

## Source Analysis Record—X'0030'

Field	Size	Description
Input record origin	XL1	<b>X'01'</b> Source line from primary input <b>X'02'</b> Source line from Macro generation. <b>X'03'</b> Source line from library member. <b>X'04'</b> Reserved <b>X'05'</b> Source line from AINSERT internal buffer.
Parent record origin	XL1	<b>X'01'</b> Source line from primary input <b>X'02'</b> Source line from Macro generation. <b>X'03'</b> Source line from library member. <b>X'04'</b> Reserved <b>X'05'</b> Source line from AINSERT internal buffer
Print flags	XL1	<b>X'80'</b> PRINT GEN <b>X'40'</b> PRINT DATA <b>X'20'</b> PRINT ON <b>X'10'</b> PRINT NOMSOURCE (0 = PRINT MSOURCE) <b>X'08'</b> PRINT UHEAD <b>X'04'</b> PRINT MCALL
	XL2	Reserved
Source record type (within source record origin)	XL1	<b>X'01'</b> Comment line that is not within a macro definition. <b>X'02'</b> Machine instruction that is not within a macro definition. <b>X'03'</b> Assembler instruction that is not within a macro definition. This includes conditional assembly instructions such as AIF and SETC. <b>X'04'</b> Macro call instruction. <b>X'05'</b> Macro definition. All statements between (and including) the MACRO prototype statement and the corresponding MEND statement. This includes nested macro definitions.
Assembler operation code	XL1	The assembler operation code for assembler instructions. (See note 2 on page 293). This field is only valid if the "Source record type" is set to X'03'.
Flags	XL1	Flag byte for address fields. <b>X'80'</b> Address 1 present <b>X'40'</b> Address 2 present
	AL4	Reserved
Address 1	AL4	The address 1 field from the assembly
	AL4	Reserved
Address 2	AL4	The address 2 field from the assembly
Offset of name entry in statement field	FL4	Zero if name entry not present or if the name begins at the beginning of the source record (see note 1 on page 293).
Length of name entry	FL4	Zero if name entry not present (see note 1 on page 293)
Offset of operation entry in statement field	FL4	Zero if operation entry not present (see note 1 on page 293)
Length of operation entry	FL4	Zero if operation entry not present (see note 1 on page 293)



Field	Size	Description
Offset of operand entry in statement field	FL4	Zero if operand entry not present (see note 1)
Length of operand entry	FL4	Zero if operand entry not present (see note 1)
Offset of remarks entry in statement field	FL4	Zero if remarks entry not present (see note 1)
Length of remarks entry	FL4	Zero if remarks entry not present (see note 1)
Offset of continuation indicator field	FL4	Zero if no continuation indicator present (see note 1)
	XL4	Reserved
Input macro or copy member name offset	FL4	The offset from the beginning of this record to the input macro or copy member name. A value of binary zeros indicates that there is no input macro or copy member name.
Input macro or copy member name length	FL4	Zero if the input record line does not come from a macro or a copy member
Parent macro or copy member name offset	FL4	The offset from the beginning of this record to the parent macro or copy member name. A value of binary zeros indicates that there is no parent macro or copy member name.
Parent macro or copy member name length	FL4	Zero if the parent record line does not come from a macro or a copy member
Source record offset	FL4	The offset from the beginning of this record to the source record.
Source record length	FL4	The length of the actual source record following
	XL8	Reserved
Input Macro or copy member name	CL(n)	The macro or copy member name if the input record originated from a macro or copy member
Parent macro or copy member name	CL(n)	The macro or copy member name if the parent record originated from a macro or copy member
Source record	CL(n)	

**Notes:**

- The length and offset fields for the name entry, operation entry, remarks entry, and continuation indicator are zero for the following statements:
  - Macro definition statements with a Source Record Type of X'04'
  - Macro definition statements with a Source Record Type of X'05'
  - EXITCTL assembler statements
  - ICTL assembler statements
- The assembler operation code field can contain the operation code values shown in Table 38 on page 294.

## Source Analysis Record—X'0030'

Table 38. Assembler operation code values

Operation Code	Assembler Instruction	Operation Code	Assembler Instruction	Operation Code	Assembler Instruction
X'00'	GBLA	X'1B'	START	X'36'	Reserved
X'01'	GBLB	X'1C'	CSECT	X'37'	MHELP
X'02'	GBLC	X'1D'	DSECT	X'38'	AREAD
X'03'	LCLA	X'1E'	COM	X'39'	Reserved
X'04'	LCLB	X'1F'	EQU	X'3A'	Reserved
X'05'	LCLC	X'20'	ORG	X'3B'	WXTRN
X'06'	SETA	X'21'	END	X'3C'	Reserved
X'07'	SETB	X'22'	LTORG	X'3D'	AMODE
X'08'	SETC	X'23'	USING	X'3E'	RMODE
X'09'	AIF	X'24'	DROP	X'3F'	RSECT
X'0A'	AGO	X'25'	ACTR	X'40'	CCW0
X'0B'	ANOP	X'26'	DC	X'41'	CCW1
X'0C'	COPY	X'27'	DS	X'42'	EXITCTL
X'0D'	MACRO	X'28'	CCW	X'43'	ASPACE
X'0E'	MNOTE	X'29'	CNOP	X'44'	AEJECT
X'0F'	MEXIT	X'2A'	LOCTR	X'45'	ALIAS
X'10'	MEND	X'2B'	DXD	X'46'	CEJECT
X'11'	ICTL	X'2C'	CXD	X'47'	ADATA
X'12'	ISEQ	X'2D'	Reserved	X'48'	SETAF
X'13'	PRINT	X'2E'	OPSYN	X'49'	SETCF
X'14'	SPACE	X'2F'	PUSH	X'4A'	CATTR
X'15'	EJECT	X'30'	POP		(z/OS & CMS)
X'16'	PUNCH	X'31'	Reserved	X'4B'	ACONTROL
X'17'	REPRO	X'32'	Reserved	X'4C'	XATTR
X'18'	TITLE	X'33'	Literal		(z/OS & CMS)
X'19'	ENTRY	X'34'	Reserved	X'4D'	AINSET
X'1A'	EXTRN	X'35'	Reserved		

## Source Error Record—X'0032'

Field	Size	Description
Statement number	FL4	The statement number of the statement in error
Error Identifier	CL16	The error message identifier
Error Severity	HL2	The severity of the error
Error message offset	FL4	The offset from the beginning of this record to the error message.
Error message length	FL4	The length of the error message text
	XL8	Reserved
Error Message	CL(n)	The error message text

### Note:

1. This record also includes MNOTEs generated by the assembler.
2. The language of the error diagnostic messages is determined by the LANGUAGE assembler option.

## DC/DS record—X'0034'

Field	Size	Description
ESDID	FL4	The ESDID for the source record.

Field	Size	Description
Type Flag	XL1	<p><b>1... ....</b> Bit 1 = Define Constant (DC, CXD, CCW, CCW0, or CCW1), Bit 0 = Define Storage (DS or DXD)</p> <p><b>.1.. ....</b> If “Define Constant” bit is set, bit 1 indicates the operand is a CXD. If “Define Constant” bit is <i>not</i> set, bit 1 indicates the operand is a DXD.</p> <p><b>...1. ....</b> If “Define Constant” bit is set, bit 1 indicates the operand is a CCW, CCW0, or CCW1.</p> <p><b>...1 ....</b> Bit 1 indicates this record is associated with an object text record (X'0035'). The object text record is created when a DC statement has a duplication factor greater than 1, and at least one of the operand values has a reference to the current location counter (*).</p> <p><b>.... 1...</b> Reserved</p> <p><b>.... .1..</b> Reserved</p> <p><b>.... ..1.</b> Reserved</p> <p><b>.... ...1</b> Reserved</p>
	XL5	Reserved
Statement Number	FL4	The statement number of the source line that generated this text, if known. Otherwise it contains zeros.
Number of operands	FL4	<p>The number of operands defined by the source record.</p> <p>The groups of nine operand fields below occur <i>n</i> times depending on the value in this field.</p>
Offset of operands	FL4	<p>The offset from the beginning of this record to the first group of operand fields. A value of binary zeros indicates that there are no operands.</p> <p><b>Start of operand group, one group per operand. The ellipses (...) indicate the fields are grouped.</b></p>
...Offset of next operand	FL4	The offset from the beginning of this record to the next group of operand fields. A value of binary zeros indicates that there are no more operands.
...Location Counter	FL4	The location counter for this operand.
...Duplication Factor	FL4	The duplication factor for this operand.
...Bit Offset	XL1	The offset within byte (0–7) for bit-length operands.
...Type Attribute	XL1	The value that the assembler Type Attribute reference returns (see “Type attribute (T)” in the <i>HLASM Language Reference</i> ).
...Type Extension	CL1	The type extension for this operand.
...Program Type	XL4	The value that the assembler SYSATTRP() internal function returns (see “SYSATTRP” in the <i>HLASM Language Reference</i> ).
	XL4	Reserved
...Number of values	FL4	<p>The number of nominal values defined by this operand.</p> <p>The groups of five nominal-value fields below occur <i>n</i> times depending on the value in this field.</p>

## DC/DS record—X'0034'

Field	Size	Description
...Offset of values	FL4	The offset from the beginning of this record to the first group of nominal-value fields. A value of binary zeros indicates that there are no nominal values.
<b>End of operand group.</b>		
<b>Start of nominal-value group, one group per value. The ellipses (.....) indicate the fields are grouped.</b>		
.....Offset of next nominal value	FL4	The offset from the beginning of this record to the next group of nominal-value fields. A value of binary zeros indicates that there are no more nominal values.
.....Value offset	FL4	The offset from the beginning of this record to the generated nominal value. A value of binary zeros indicates that there is no generated nominal value.
.....Byte length	FL4	The byte length of the nominal value, if defined with a byte length.
.....Bit length	FL4	The bit length of the nominal value, if defined with a bit length.
.....Nominal value	XL(n)	<p>If this record describes a DC, CXD, CCW, CCW0, or CCW1, then the value contains the nominal value. (A DC with a zero duplication factor is treated the same as a DS and this field is not present). If this record describes a DS or DXD, this field is not present.</p> <p>If a byte length is specified (or implied), the value contains the number of bytes specified. The value field is aligned according to the operand type. For example, hexadecimal values are left-aligned and packed values are right-aligned.</p> <p>If a bit length is specified, the length of the value is the number of bytes required to contain the required bits. For example, if the bit length was 10, the value is 2 bytes in length. The value is in the leftmost 10 bits. Alignment within the specified number of bits is according to the operand type. For example, hexadecimal values are left-aligned and packed values are right-aligned.</p>
<b>End of nominal-value group.</b>		

### Note:

- Only one of the two fields for byte/bit lengths contains a non-zero value. This means that there is a byte length, or a bit length, but not both.
- No description of any inter-statement boundary alignment padding is produced. Any padding because of alignment can be calculated by comparing the location counter of the current operand with the sum of the location counter and length of the previous operand.  
The length of the previous operand would need to be calculated using the duplication factor, number of nominal values, and the length of each nominal value.
- High Level Assembler creates the DC Extension record X'0035' when the duplication factor is greater than 1 and at least one of the operand values has a reference to the current location counter (\*).  
See Example 6, page 300.
- Where the number of operands would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of operands (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent operands. The count of the number of operands is a count for the current record.  
Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.

The following examples show the format of a DC/DS Record for various DC statements.

1. EXAMPLE1 DC 3F'5,6',HP(X'05')'7'

```

ESDID                : F'1'
Type Flag             : B'10000000'
Reserved              : X'0000000000'
Statement Number      : F'2'
Number of Operands    : F'2'
Offset of first Operand : F'38'

Offset of next Operand : F'108'
Location Counter       : X'00000000'
Duplication Factor     : F'3'
Bit Offset             : B'00000000'
Type Attribute         : C'F'
Type Extension         : C' '
Program Type           : X'00000000'
Reserved               : X'00000000'
Number of values       : F'2'
Offset of first value  : F'68'

Offset of next value   : F'88'
Offset of generated value : F'84'
Byte length            : F'4'
Bit length             : F'0'
Generated Value        : X'00000005'

Offset of next value   : F'0'
Offset of generated value : F'104'
Byte length            : F'4'
Bit length             : F'0'
Generated Value        : X'00000006'

Offset of next Operand : F'0'
Location Counter       : X'00000018'
Duplication Factor     : F'1'
Bit Offset             : B'00000000'
Type Attribute         : C'H'
Type Extension         : C' '
Program Type           : X'00000005'
Reserved               : X'00000000'
Number of values       : F'1'
Offset of first value  : F'138'

Offset of next value   : F'0'
Offset of generated value : F'154'
Byte length            : F'2'
Bit length             : F'0'
Generated Value        : X'0007'

```

2. EXAMPLE2 DC P'5,927'

```

ESDID                : F'1'
Type Flag             : B'10000000'
Reserved              : X'0000000000'
Statement Number      : F'3'
Number of Operands    : F'1'
Offset of first Operand : F'38'

Offset of next Operand : F'0'
Location Counter       : X'0000001A'
Duplication Factor     : F'1'
Bit Offset             : B'00000000'
Type Attribute         : C'P'
Type Extension         : C' '
Program Type           : X'00000000'
Reserved               : X'00000000'
Number of values       : F'2'

```

Offset of first value : F'68'

Offset of next value : F'85'  
 Offset of generated value : F'84'  
 Byte length : F'1'  
 Bit length : F'0'  
 Generated Value : X'5C'

Offset of next value : F'0'  
 Offset of generated value : F'101'  
 Byte length : F'2'  
 Bit length : F'0'  
 Generated Value : X'927C'

### 3. EXAMPLE3 DC B'101',2B'10111'

ESDID : F'1'  
 Type Flag : B'10000000'  
 Reserved : X'0000000000'  
 Statement Number : F'4'  
 Number of Operands : F'2'  
 Offset of first Operand : F'38'

Offset of next Operand : F'85'  
 Location Counter : X'0000001D'  
 Duplication Factor : F'1'  
 Bit Offset : B'00000000'  
 Type Attribute : C'B'  
 Type Extension : C' '  
 Program Type : X'00000000'  
 Reserved : X'00000000'  
 Number of values : F'1'  
 Offset of first value : F'68'

Offset of next value : F'0'  
 Offset of generated value : F'84'  
 Byte length : F'1'  
 Bit length : F'0'  
 Generated Value : X'05'

B'00000101'

Offset of next Operand : F'0'  
 Location Counter : X'0000001E'  
 Duplication Factor : F'2'  
 Bit Offset : B'00000000'  
 Type Attribute : C'B'  
 Type Extension : C' '  
 Program Type : X'00000000'  
 Reserved : X'00000000'  
 Number of values : F'1'  
 Offset of first value : F'115'

Offset of next value : F'0'  
 Offset of generated value : F'131'  
 Byte length : F'1'  
 Bit length : F'0'  
 Generated Value : X'17'

B'00010111'

### 4. EXAMPLE4 DC BL.3'101',BL.5'10111,11001'

ESDID : F'1'  
 Type Flag : B'10000000'  
 Reserved : X'0000000000'  
 Statement Number : F'5'  
 Number of Operands : F'2'  
 Offset of first Operand : F'38'

Offset of next Operand : F'85'  
 Location Counter : X'00000020'  
 Duplication Factor : F'1'  
 Bit Offset : B'00000000'

```

Type Attribute      : C'B'
Type Extension     : C' '
Program Type       : X'00000000'
Reserved          : X'00000000'
Number of values   : F'1'
Offset of first value : F'68'

      Offset of next value      : F'0'
      Offset of generated value : F'84'
      Byte length              : F'0'
      Bit length               : F'3'
      Generated Value           : X'A0'                B'10100000'

Offset of next Operand : F'0'
Location Counter       : X'00000020'
Duplication Factor     : F'1'
Bit Offset             : B'00000011'
Type Attribute        : C'B'
Type Extension        : C' '
Program Type          : X'00000000'
Reserved              : X'00000000'
Number of values      : F'2'
Offset of first value  : F'115'

      Offset of next value      : F'132'
      Offset of generated value : F'131'
      Byte length              : F'0'
      Bit length               : F'5'
      Generated Value           : X'B8'                B'10111000'

      Offset of next value      : F'0'
      Offset of generated value : F'148'
      Byte length              : F'0'
      Bit length               : F'5'
      Generated Value           : X'C8'                B'11001000'

```

##### 5. EXAMPLE5 DC LB'4',2L'9'

This example shows a DC statement that requires the type extension field to differentiate the attributes of the two floating point operands.

```

ESDID              : F'1'
Type Flag           : B'10000000'
Reserved           : X'0000000000'
Statement Number    : F'6'
Number of Operands  : F'2'
Offset of first Operand : F'38'

      Offset of next Operand : F'100'
      Location Counter       : X'00000028'
      Duplication Factor     : F'1'
      Bit Offset             : B'00000000'
      Type Attribute        : C'L'
      Type Extension        : C'B'
      Program Type          : X'00000000'
      Reserved              : X'00000000'
      Number of values      : F'1'
      Offset of first value  : F'68'

      Offset of next value      : F'0'
      Offset of generated value : F'84'
      Byte length              : F'16'
      Bit length               : F'0'
      Generated Value         : X'40010000000000000000000000000000'

Offset of next Operand : F'0'
Location Counter       : X'00000038'
Duplication Factor     : F'2'
Bit Offset             : B'00000000'
Type Attribute        : C'L'

```

## DC/DS record—X'0034'

```
Type Extension      : C' '  
Program Type       : X'00000000'  
Reserved          : X'00000000'  
Number of values   : F'1'  
Offset of first value : F'130'  
  
Offset of next value : F'0'  
Offset of generated value : F'146'  
Byte length         : F'16'  
Bit length          : F'0'  
Generated Value     : X'41900000000000003300000000000000'
```

### 6. EXAMPLE6 DC 5Y(\*-2),5Y(\*-1)

This example shows a DC statement that requires a DC extension record (X'0035') to contain the repeating fields.

The object code generated, and shown in the assembler listing:

```
                                2      PRINT DATA  
000000 FFFE000000020004      3      DC    5Y(*-2),5Y(*-1)  
000008 00060009000B000D  
000010 000F0011
```

The ADATA records produced:

```
ESDID                  : F'1'  
Type Flag              : B'10010000'  
Reserved               : X'0000000000'  
Statement Number       : F'3'  
Number of Operands     : F'2'  
Offset of first Operand : F'38'  
  
Offset of next Operand : F'86'  
Location Counter       : X'00000000'  
Duplication Factor     : F'5'  
Bit Offset             : B'00000000'  
Type Attribute         : C'Y'  
Type Extension         : C' '  
Program Type           : X'00000000'  
Reserved               : X'00000000'  
Number of values       : F'1'  
Offset of first value  : F'130'  
  
Offset of next value   : F'0'  
Offset of generated value : F'84'  
Byte length           : F'2'  
Bit length            : F'0'  
Generated Value       : X'FFFE'  
  
Offset of next Operand : F'86'  
Location Counter       : X'00000000A'  
Duplication Factor     : F'5'  
Bit Offset             : B'00000000'  
Type Attribute         : C'Y'  
Type Extension         : C' '  
Program Type           : X'00000000'  
Reserved               : X'00000000'  
Number of values       : F'1'  
Offset of first value  : F'116'  
  
Offset of next value   : F'0'  
Offset of generated value : F'132'  
Byte length           : F'2'  
Bit length            : F'0'  
Generated Value       : X'0009'
```

The object text for the statement is in the following DC Extension Record:

```
ESDID                  : F'1'  
Statement Number       : F'3'  
Location Counter       : F'0'
```



```

Reserved           : X'0000000000000000'
Offset of Object   : F'44'
Length of Object   : F'20'
Object Text        : X'FFFE00000002000400060009000B000D000F0011'

```

## DC Extension Record—X'0035'

Field	Size	Description
ESDID	FL4	The ESDID for the record
Statement number	FL4	The statement number of the source line that generated this text, if known. Zero otherwise.
Location Counter	FL4	Address (offset) of the text within the module
	XL8	Reserved
Object text offset	FL4	The offset from the beginning of this record to the generated object text.
Object text length	FL4	The length of the following object text
Object text	XL(n)	The actual object text

### Note:

Where the amount of object text would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current length of the object text (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent object text. The length of the object text is the length for the current record.

Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces. The exception is the location counter field which will contain the correct location for the start of the continued object text.

## Machine Instruction Record—X'0036'

Field	Size	Description
ESDID	FL4	The ESDID for the machine instruction record
Statement number	FL4	The statement number of the source record
Location Counter	FL4	The location counter for this instruction
	XL8	Reserved
Instruction offset	FL4	The offset from the beginning of this record to the machine instruction.
Instruction length	FL4	The length of the machine instruction
Value of Instruction	XL(n)	The actual value of the machine instruction

## Relocation Dictionary Record—X'0040'

Field	Size	Description
POS.ID	FL4	The external symbol dictionary ID number assigned to the ESD entry for the control section in which the address constant is used as an operand.
REL.ID	FL4	The external symbol dictionary ID number assigned to the ESD entry for the control section in which the referenced symbol is defined.

## Relocation Dictionary Record—X'0040'

Field	Size	Description
	AL4	Reserved
Address	AL4	The assembled address of the field where the address constant is stored. Not all relocation types supported by GOFF object files are reported in the Relocation Dictionary Record.
Flags	XL1	<b>x...</b> .... Reserved <b>.1..</b> .... Add 4 to length of ADCON <b>..11</b> .... ADCON type - CXD (3) <b>..10</b> .... ADCON type - Q (2) <b>..01</b> .... ADCON type - V (1) <b>..00</b> .... ADCON type - A (0) <b>.... 11..</b> Contains length-1 of ADCON <b>.... ..1.</b> Relocation sign: 1 = -, 0 = + <b>.... ...1</b> Following RLD item has same R and P pointer

## Symbol Record—X'0042'

Field	Size	Description
ESDID	FL4	ESDID of the section in which the symbol is defined. This is zero for an undefined symbol type.
Statement Number	FL4	The number of the statement in which the symbol is defined. This is zero for an undefined symbol type.
Location Counter	FL4	Contains the offset from the start of the DSECT, the non-relocated address of the instruction belonging to this symbol in a CSECT (this is not always the offset from the start of the CSECT), or the value of the equate. This is zero for an undefined symbol type.
Symbol Type	XL1	<b>X'00'</b> Undefined name <b>X'01'</b> CSECT / RSECT name <b>X'02'</b> DSECT name <b>X'03'</b> Common section name <b>X'04'</b> Dummy External DSECT name (DXD) <b>X'05'</b> V-type constant name <b>X'06'</b> Qualifier <b>X'07'</b> EXTRN/WXTRN name <b>X'08'</b> LOCTR name <b>X'09'</b> Duplicate name <b>X'0A'</b> Literal name <b>X'0B'</b> *-in-literal name <b>X'0C'</b> EQU name <b>1</b> <b>X'0D'</b> Ordinary label <b>X'0E'</b> Unresolvable EQU, DC or DS symbol
Duplication Factor	FL4	Number of times the first operand field named by the symbol occurs. This is zero for an undefined symbol type.
Type Attribute	XL1	The value that the assembler Type Attribute reference returns (see "Type attribute (T)" in the <i>HLASM Language Reference</i> ).
Assembler Type	CL4	The value that the assembler SYSATTR() internal function returns (see "SYSATTR" in the <i>HLASM Language Reference</i> ).

Field	Size	Description
Program Type	XL4	The value that the assembler SYSATTRP() internal function returns (see “SYSATTRP” in the <i>HLASM Language Reference</i> ).
Length attribute	FL4	Length in bytes, either specified or by default.
Integer attribute	HL2	Number of positions occupied by the integer portion of fixed-point and decimal constants in their object code form. This is zero for an undefined symbol type.
Scaling attribute	HL2	Number of positions occupied by the fractional portion of fixed-point and decimal constants in their object code form. This is zero for an undefined symbol type.
Symbol Flags	XL1	<b>1... ..</b> Bit 1 = 1, the symbol is relocatable, Bit 0 = the symbol is absolute. This bit is zero for an undefined symbol type.
		<b>11.. ..</b> Complex relocatable
		<b>..1. ....</b> Reserved
		<b>...1 ....</b> Reserved
		<b>.... 1...</b> Reserved
		<b>.... .1..</b> Reserved
		<b>.... ..1.</b> Reserved
		<b>.... ...1</b> Reserved
	XL7	Reserved
Symbol name offset	FL4	The offset from the beginning of this record to the symbol name.
Symbol name length	FL4	Number of characters in the symbol name
Symbol name	CL(n)	The symbol name.

**Note:**

For record type “EQU” specified at **1**, where the “EQU” is for a relocatable value, the ESDID of the “EQU” is provided. Where the “EQU” is non-relocatable, the ESDID of the section in control will be provided. The symbol flags can be checked to determine whether the “EQU” is relocatable or absolute.

## Symbol and Literal Cross Reference Record—X'0044'

Field	Size	Description
Statement Number	FL4	The statement number where the symbol or literal is defined or declared
Relocatability Type	CL1	<b>C' '</b> Simple relocatable symbol
		<b>C'A'</b> Absolute symbol
		<b>C'C'</b> Complex relocatable symbol
	XL7	Reserved
Name offset	FL4	The offset from the beginning of this record to the symbol or literal name.
Name length	FL4	The length of the symbol or literal name
Total references	FL4	The total number of references to the symbol or literal for the assembly

### Symbol and Literal Cross Reference Record—X'0044'

Field	Size	Description
Number of references	FL4	The number of references to the symbol or literal in this record  The groups of two reference fields below occur $n$ times depending on the value in this field. The reference groups are contiguous so they may be treated as an array.
Offset of references	FL4	The offset from the beginning of this record to the first group of reference fields. A value of binary zeros indicates that there are no references.
Name	CL(n)	The symbol or literal name.
<b>Start of reference groups, one group per reference. The ellipses (...) indicate the fields are grouped.</b>		
...Statement Number	FL4	The statement number on which the symbol or literal is referenced
...Reference Flag	CL1	<b>C' '</b> No branch or modification <b>C'M'</b> Modification <b>C'B'</b> Branched to <b>C'U'</b> USING statement <b>C'D'</b> DROP statement <b>C'X'</b> Execute Instruction
<b>End of reference groups.</b>		

**Note:**

Where the number of references would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of references (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent references. The count of the number of references is a count for the current record.

Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.

### Register Cross Reference Record—X'0045'

Field	Size	Description
Register number	XL1	The register number (X'0' to X'F')
Register Type	CL1	G—General
	XL2	Reserved
Total references	FL4	The total number of references to the register for the assembly
Number of references	FL4	The number of references to the register in this record  The groups of two reference fields below occur $n$ times depending on the value in this field. The reference groups are contiguous so they may be treated as an array.
Offset of references	FL4	The offset from the beginning of this record to the first group of reference fields. A value of binary zeros indicates that there are no references.
<b>Start of reference groups, one group per reference. The ellipses (...) indicate the fields are grouped.</b>		

## Register Cross Reference Record—X'0045'

Field	Size	Description
...Statement Number	FL4	The statement number on which the register is referenced
...Reference Flag	CL1	<b>C' '</b> No branch or modification <b>C'M'</b> Modification <b>C'B'</b> Branched to <b>C'U'</b> USING statement <b>C'D'</b> DROP statement <b>C'N'</b> Index register
<b>End of reference groups.</b>		

### Note:

Where the number of references would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of references (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent references. The count of the number of references is a count for the current record.

Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.

## Library Record—X'0060'

Field	Size	Description
Concatenation number	FL4	The library concatenation number
Library name offset	FL4	The offset from the beginning of this record to the library (file) name
Library name length	FL4	The length of the library (file) name
Volume serial number offset	FL4	The offset from the beginning of this record to the volume serial number
Volume serial number length	FL4	The length of the volume serial number
DDNAME offset	FL4	The offset from the beginning of this record to the DDNAME
DDNAME length	FL4	The length of the DDNAME
Number of members	FL4	The number of macros and copy code members in this record  The groups of three member fields below occur <i>n</i> times depending on the value in this field.
Offset of members	FL4	The offset from the beginning of this record to the first group of member fields. A value of binary zeros indicates that there are no members.
Library name	CL(n)	The name of the library (file) from which the macro or copy member was retrieved, or "PRIMARY INPUT" for an in-stream macro. Under z/VSE, this field contains the library and sublibrary name.
Volume serial number	CL(n)	The volume serial number of the (first) volume on which the library resides
DDNAME	CL(n)	The DDNAME of the library.
<b>Start of member groups, one group per member. The ellipses (...) indicate the fields are grouped.</b>		

## Library Record—X'0060'

Field	Size	Description
...Offset of next member	FL4	The offset from the beginning of this record to the next group of member fields. A value of binary zeros indicates that there are no more members.
...Member name offset	FL4	The offset from the beginning of this record to the macro or copy code member name
...Member name length	FL4	The length of the macro or copy code member name
...Member name	CL(n)	The name of the macro or copy code member that has been used. If the source is "PRIMARY INPUT", then this field contains the macro name from the source program.
End of member groups.		

### Note:

1. If a LIBRARY user exit has been specified for the assembly, and the LIBRARY user exit has opened the Library data set, the record contains the library names returned by the user exit.
2. Where the number of members would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of members (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent members. The count of the number of members is a count for the current record.  
Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.

## Library Member and Macro Cross Reference Record—X'0062'

Field	Size	Description
Concatenation Number	FL4	The concatenation number of the library or primary input file
Statement Number	FL4	The statement number is: <b>0</b> When the member or macro is retrieved from a library <b>&gt;0</b> When the macro is defined in the primary input file. It represents the statement number where the macro is defined.
Concatenation Type	CL1	<b>C'L'</b> Concatenation number refers to a library <b>C'P'</b> Concatenation number refers to the primary input
Statement Definition Flag	CL1	<b>C'X'</b> The macro is read from the library and imbedded in the primary source, using the LIBMAC option <b>C' '</b> The flag is usually blank except in special cases, as described above
	XL8	Reserved
Member or macro name offset	FL4	The offset from the beginning of this record to the member or macro name
Member or macro name length	FL4	The length of the member or macro name
Parent name offset	FL4	The offset from the beginning of this record to the parent (caller) member or macro name
Parent name length	FL4	The length of the parent (caller) member or macro name

## Library Member and Macro Cross Reference Record—X'0062'

Field	Size	Description
Total references	FL4	The total number of references to the member or macro for the assembly
Number of references	FL4	The number of references to the member or macro by the parent.  The groups of two reference fields below occur <i>n</i> times depending on the value in this field. The reference groups are contiguous so they may be treated as an array.
Offset of references	FL4	The offset from the beginning of this record to the first group of reference fields. A value of binary zeros indicates that there are no references.
Member or macro name	CL(n)	The name of the member or macro.
Parent macro name	CL(n)	The name of the macro that called this macro or issued the COPY instruction. This field contains "PRIMARY INPUT" when the member or macro is called directly from the primary input file.
<b>Start of reference groups, one group per reference. The ellipses (...) indicate the fields are grouped.</b>		
...Statement Number	FL4	The statement number on which the member is copied or included, or the statement number on which the macro is called
...Reference Flag	CL1	<div> <div>C' '</div> <div>Blank means the reference is caused by a macro call</div> <div>C'C'</div> <div>Reference is caused by a COPY instruction</div> </div>
<b>End of reference groups.</b>		

### Note:

Where the number of references would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of references (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent references. The count of the number of references is a count for the current record.

Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.

## User-supplied Information Record—X'0070'

Field	Size	Description
User field 1	XL4	User-specified binary data
User field 2	XL4	User-specified binary data
User field 3	XL4	User-specified binary data
User field 4	XL4	User-specified binary data
User data offset	FL4	The offset from the beginning of this record to the user data
User data length	FL4	The length of the user data
User data	CL(n)	User-specified character data

**USING Map Record—X'0080'**

Field	Size	Description
Record type	XL1	<b>X'00'</b> USING record <b>X'20'</b> POP record <b>X'40'</b> PUSH record <b>X'80'</b> DROP record
USING Flag	XL1	USING type (ORDINARY, LABELED, DEPENDENT, LABELED DEPENDENT) <b>X'00'</b> Ordinary USING <b>X'10'</b> Labeled USING <b>X'20'</b> Dependent USING <b>X'30'</b> Labeled Dependent USING
Location ESDID	FL4	The value of the ESDID of the current section when the USING, DROP, PUSH USING, or POP USING was issued
Statement number	FL4	The statement number of the USING, DROP, PUSH USING, or POP USING
Location Counter	FL4	The value of the location counter when the USING, DROP, PUSH USING, or POP USING was issued
USING value	FL4	The value of the USING statements first-operand expression. This is zero for PUSH, POP, and DROP.
Last statement	FL4	The last statement number for which this base-register was used in converting a symbolic address into its base-displacement form. This is zero for PUSH, POP, and DROP.
USING ESDID	FL4	For ordinary and labeled USING instructions, this field indicates the ESDID of the section specified on first operand of the USING statement. For dependent USING instructions, this field indicates the ESDID of the section specified on the corresponding ordinary USING instruction that is used to resolve the address. This is zero for PUSH, POP, and DROP.
Register	XL1	The register used in the USING. This is zero for PUSH and POP. Where a DROP with no operand or a DROP ALL is specified, this field contains X'FF'.
Displacement	XL2	The maximum displacement for this USING register. This is zero for PUSH, POP, and DROP.
	XL1	Reserved
USING range	FL4	The value of the USING range.
	XL2	Reserved
Label offset	FL4	The offset from the beginning of this record to the label and USING text. A value of binary zeros indicates that there is no label or USING text.
Label length	FL4	The length of the label and USING text. This length field is rounded up to a doubleword boundary. Hence if the text was 13 bytes in length, the length would be set at 16 and the text space padded on the right. This is zero for PUSH and POP.
Label	CL(n)	The source text for the label and USING from the source USING record. This field is null for PUSH and POP.



**Statistics record—X'0090'**

Field	Size	Description
Buffer pool allocation	FL4	The number of Kilobytes (KB) of storage allocated to the buffer pool.
Required In-storage	FL4	The number of Kilobytes (KB) of storage required to make the assembly an in-storage assembly.
Primary input records	FL4	The number of primary input records read for the assembly row.
Library records	FL4	The number of library records read for the assembly row.
Work file reads	FL4	The number of work file reads for the assembly row.
Print records written	FL4	The number of print records written for the assembly row.
Object records written	FL4	The number of object records written for the assembly row.
Work file writes	FL4	The number of work file writes for the assembly row.
ADATA file writes	FL4	The number of associated data (ADATA) file writes for the assembly.
ADATA calls	FL4	The number of calls to the associated data (ADATA) exit.  This field is zero if no exit is present.
ADATA added records	FL4	The number of records added by the associated data (ADATA) exit.  This field is zero if no exit is present.
ADATA deleted records	FL4	The number of records deleted by the associated data (ADATA) exit.  This field is zero if no exit is present.
ADATA diagnostic messages	FL4	The number of diagnostic messages returned by the associated data (ADATA) exit.  This field is zero if no exit is present.
Library calls	FL4	The number of calls to the LIBRARY exit  This field is zero if no exit is present.
Library added records	FL4	The number of records added by the LIBRARY exit  This field is zero if no exit is present.
Library deleted records	FL4	The number of records deleted by the LIBRARY exit  This field is zero if no exit is present.
Library diagnostic messages	FL4	The number of diagnostic messages returned by the LIBRARY exit  This field is zero if no exit is present.
Listing calls	FL4	The number of calls to the LISTING exit  This field is zero if no exit is present.
Listing added records	FL4	The number of records added by the LISTING exit  This field is zero if no exit is present.

## Statistics record—X'0090'

Field	Size	Description
Listing deleted records	FL4	The number of records deleted by the LISTING exit  This field is zero if no exit is present.
Listing diagnostic messages	FL4	The number of diagnostic messages returned by the LISTING exit  This field is zero if no exit is present.
Object calls	FL4	The number of calls to the OBJECT exit. (z/OS and CMS)  This field is zero if no exit is present.  Reserved (z/VSE)
Object added records	FL4	The number of records added by the OBJECT exit. (z/OS and CMS)  This field is zero if no exit is present.  Reserved (z/VSE)
Object deleted records	FL4	The number of records deleted by the OBJECT exit. (z/OS and CMS)  This field is zero if no exit is present.  Reserved (z/VSE)
Object diagnostic messages	FL4	The number of diagnostic messages returned by the OBJECT exit. (z/OS and CMS)  This field is zero if no exit is present.  Reserved (z/VSE)
Source calls	FL4	The number of calls to the SOURCE exit  This field is zero if no exit is present.
Source added records	FL4	The number of records added by the SOURCE exit  This field is zero if no exit is present.
Source deleted records	FL4	The number of records deleted by the SOURCE exit  This field is zero if no exit is present.
Source diagnostic messages	FL4	The number of diagnostic messages returned by the SOURCE exit  This field is zero if no exit is present.
Punch calls	FL4	The number of calls to the PUNCH exit  This field is zero if no exit is present.
Punch added records	FL4	The number of records added by the PUNCH exit  This field is zero if no exit is present.
Punch deleted records	FL4	The number of records deleted by the PUNCH exit  This field is zero if no exit is present.

Field	Size	Description
Punch diagnostic messages	FL4	The number of diagnostic messages returned by the PUNCH exit  This field is zero if no exit is present.
Term calls	FL4	The number of calls to the TERM exit  This field is zero if no exit is present.
Term added records	FL4	The number of records added by the TERM exit  This field is zero if no exit is present.
Term deleted records	FL4	The number of records deleted by the TERM exit  This field is zero if no exit is present.
Term diagnostic messages	FL4	The number of diagnostic messages returned by the TERM exit  This field is zero if no exit is present.
Assembly start time	FL4	The local time when the assembly commenced. This time is recorded after data set allocation, storage allocation, invocation parameter processing, and other initialization processing.  Stored in packed format as <i>hhmmssstt</i> : <i>hh</i> The hour <i>mm</i> The minute <i>ss</i> The second <i>t</i> Tenths of a second <i>h</i> Hundredths of a second
Assembly stop time	FL4	The local time when the assembly completed  Stored in packed format as <i>hhmmssstt</i> : <i>hh</i> The hour <i>mm</i> The minute <i>ss</i> The second <i>t</i> Tenths of a second <i>h</i> Hundredths of a second
Processor time	FL4	The number of processor seconds utilized by this assembly. (z/OS and CMS)  The low order bit represents 1 microsecond.  Reserved (z/VSE)
ASMAOPT input records	FL4	The number of ASMAOPT input records read for the assembly
	XL4	Reserved
Number of functions	FL4	The number of external functions in this record  The groups of eight external-function fields below occur <i>n</i> times depending on the value in this field.
Offset of functions	FL4	The offset from the beginning of this record to the first group of external-function fields. A value of binary zeros indicates that there are no external functions.  <b>Start of external-function groups, one group per function.</b> <b>The ellipses (...) indicate the fields are grouped.</b>

## Statistics record—X'0090'

Field	Size	Description
...Offset of next external function	FL4	The offset from the beginning of this record to the next group of external-function fields. A value of binary zeros indicates that there are no more external functions.
...	XL4	Reserved
...SETAF function calls	FL4	The number of times the function was called from a SETAF assembler instruction.
...SETCF function calls	FL4	The number of times the function was called from a SETCF assembler instruction.
...Messages issued	FL4	The number of times the function requested that a message be issued
...Messages severity	HL2	The maximum severity for the messages issued by this function
...External function name offset	FL4	The offset from the beginning of this record to the external function name
...External function name length	FL4	The length of the external function name
...External function name	CL(n)	The external function module name
End of external-function groups.		

### Note:

Where the number of functions would exceed the record size for the associated data file, the record is continued on the next record. The continuation flag is set in the common header section of the record. The current number of functions (for that record) is stored in the record and the record written to the associated data file. The next record contains the subsequent functions. The count of the number of functions is a count for the current record.

Fields that have been written will not be repeated in the next record. Fixed length fields will be initialized to binary zeros or spaces, and variable length fields will have a length of binary zeros.

---

## Appendix E. Sample program

The sample program included with High Level Assembler is described in this appendix. This program demonstrates some basic assembler language, macro, and conditional assembly features, most of which are unique to High Level Assembler. The highlighted characters in the descriptions below refer to corresponding characters in the listing that precedes the descriptions.

For more details about this program, see “ASMASAMP” in the *HLASM Installation and Customization Guide*.

---

High Level Assembler Option Summary

Page 1

HLASM R6.0 2008/07/11 17.48

No Overriding ASMAOPT Parameters  
No Overriding Parameters  
No Process Statements

Options for this Assembly

NOADATA  
ALIGN  
NOASA  
BATCH  
CODEPAGE(047C)  
NOCOMPAT  
NODBCS  
NODECK  
DXREF  
ESD  
NOEXIT  
FLAG(0,ALIGN,CONT,EXLITW,NOIMPLEN,NOPAGE0,PUSH,RECORD,NOSUBSTR,USING0)  
NOFOLD  
NOGOFF  
NOINFO  
LANGUAGE(EN)  
NOLIBMAC  
LINECOUNT(60)  
LIST(121)  
MACHINE(,NOLIST)  
MXREF(SOURCE)  
OBJECT  
OPTABLE(UNI,NOLIST)  
NOPCONTROL  
NOPESTOP  
NOPROFILE  
NORA2  
NORENT  
RLD  
RXREF  
SECTALGN(8)  
SIZE(MAX)  
NOSUPRWARN  
SYSPARM()  
NOTERM  
NOTEST  
THREAD  
NOTRANSLATE  
TYPECHECK(MAGNITUDE,REGISTER)  
USING(NOLIMIT,MAP,WARN(15))  
XREF(SHORT,UNREFS)

No Overriding DD Names

---

## Sample program

BIGNAME	Symbol	Type	Id	Address	Length	Owner	Id	Flags	Alias-of	External Symbol Dictionary	Page	2
A	SD	00000001	00000000	000000DE				00		HLASM R6.0 2008/07/11 17.48		
PD2	CM	00000002	00000000	00000814				00	<b>A</b>			

BIGNAME Sample program. 1ST TITLE statement has no name, 2ND one does Page 3

Active Usings: None	Loc	Object	Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11 17.48
						2	*****		00002000
						3	* Licensed Materials - Property of IBM	*	00003000
						4	*	*	00004000
						5	* 5696-234 5647-A01	*	00005000
						6	*	*	00006000
						7	* (C) Copyright IBM Corp. 1992, 2000. All Rights Reserved.	*	00007000
						8	*	*	00008000
						9	* US Government Users Restricted Rights - Use,	*	00009000
						10	* duplication or disclosure restricted by GSA ADP	*	00010000
						11	* Schedule Contract with IBM Corp.	*	00011000
						12	*	*	00012000
						13	*****		00013000
						14	*****		00014000
						15	* DISCLAIMER OF WARRANTIES	*	00015000
						16	* The following enclosed code is sample code created by IBM	*	00016000
						17	* Corporation. This sample code is licensed under the terms of	*	00017000
						18	* the High Level Assembler license, but is not part of any	*	00018000
						19	* standard IBM product. It is provided to you solely for the	*	00019000
						20	* purpose of demonstrating the usage of some of the features of	*	00020000
						21	* High Level Assembler. The code is not supported by IBM and	*	00021000
						22	* is provided on an "AS IS" basis, without warranty of any kind.	*	00022000
						23	* IBM shall not be liable for any damages arising out of your	*	00023000
						24	* use of the sample code, even if IBM has been advised of the	*	00024000
						25	* possibility of such damages.	*	00025000
						26	*****		00026000
000000			00000	000DE		27	a csect		00027000
			R:8	00000		28	using *,8		00028000
000000	1BFF					29	sr 15,15 Set return code to zero		00029000
000002	07FE					30	br 14 and return.		00030000
						32	*****		00032000
						33	* PUSH and POP statements	*	00033000
						34	* Push down the PRINT statement, replace it, retrieve original	*	00034000
						35	*****		00035000
						37	push print Save Default setting ' PRINT ON,NODATA,GEN'		00037000
						38	print nogen,data		00038000
000004	0A23					39	wto mf=(E,1))	Expansion not shown	00039000

**A** The external symbol dictionary shows a named common statement. The named common section is defined in statement 216.

**B** Statement 37: Save the current status of the PRINT statement.

Statement 38: Modify the print options to DATA and NOGEN.

Statement 39: Macro call; note that the expansion (statements 40 and 41) is not printed.

Statement 42: All 28 bytes of data are displayed to the two-operand DC.

Statement 43: Restore earlier status of PRINT.

Statement 45: This statement is not printed. It is a nested macro call. The MCALL operand of the PRINT instruction or the PCONTROL assembler option control the printing of nested macro calls.

Statements 46: The generated output of the macro WTO is shown, but only two bytes of data are shown.

```

000006 01230ABC0102030A      C 42 dc x'123,ABC',(reallylongsymbol-transylvania)b'1,10,11,1010,1011,1100' 00040000
00000E 0B0C0102030A0B0C
000016 0102030A0B0C0102
00001E 030A0B0C

000022 0A23
000024 01230ABC0102030A

000040 5850 80AC      000AC 43      pop      print      Restore default PRINT setting      00041000
0000AC      000AC 000DE 44      wto      mf=(E,(1))      Expansion shown      00042000
0000AC 00000005      46+      SVC      35      ISSUE SVC 35      @L2C 01-WT0
BIGNAME Sample program. 1ST TITLE statement has no name, 2ND one does      47 dc x'123,ABC',(reallylongsymbol-transylvania)b'1,10,11,1010,1011,1100' 00043000
Active Usings: a,R8      49 *****      00045000
Loc Object Code Addr1 Addr2 Stmt Source Statement      HLASM R6.0 2008/07/11 17.48
000044      00000 000DE 50 *      LOCTR instruction      *      00046000
1      51 * LOCTR allows 'REMOTE' assembly of constant      *      00047000
52 *****      00048000
54      1      5,constant      00050000
D 55 deecees loctr      00051000
56 constant dc f'5'      Constant coded here, assembled behind LOCTR A      00052000
Page 4
000046 0000
000048 413243F6A8885A30
000050 338D313198A2E037

000B0 00002      E 66 &type      setc t'a7      00062000
67 a8      equ b5,l'a5,c'&type'      00063000
+a8      equ b5,l'a5,c'L'      00063000

```

**C** Statements 42 and 47: Multiple constants are allowed in hexadecimal and binary DC operands, and neither symbol in the duplication factor has been defined yet. Definition occurs in statements 144 and 145.

**D** Statements 55, 57, 194, 212 and 213 show use of the LOCTR assembler instruction. This feature allows you to break down control sections into “subcontrol” sections. It can be used in CSECT, RSECT, DSECT, and COM sections. LOCTR has many of the features of a control section; for example, all of the first LOCTR in a section is assigned space, then the second, and so on. The name of the control section automatically names the first LOCTR section. Thus LOCTR A is begun, or continued, at statements 27, 57, and 213. The location counter value shown each time is the continued value of the LOCTR. On the other hand, various LOCTR sections within a control section have common addressing as far as USING statements are concerned, subject to the computed displacement falling within 0 through 4095. In the sample, CONSTANT (at statement 56) is in LOCTR DEECEEES but the instruction referring to it (statement 54) has no addressing problems.

**E** Three-operand EQU. Here, we assign: (a) the value of B5 (not yet defined) to A8, (b) the length attribute of A5 to A8, and (c) the type attribute of A7 to A8. If no second or third operand is present in an EQU statement, the type attribute is U and the length attribute is that of the first term in the operand expression. Symbols present in the operand field must be previously defined. You cannot express the type attribute of A7 directly in the EQU statement. The EQU statement at 67 could have been written

```

a8      equ      b5,2,c'L'
a8      equ      b5,x'2',x'D3'

```

## Sample program

---

```
BIGNAME Sample program. 1ST TITLE statement has no name, 2ND one does
Active Usings: a,R8
Loc Object Code Addr1 Addr2 Stmt Source Statement HLLASM R6.0 2008/07/11 17.48
69 ***** 00065000
70 * Implicit declaration of locals &A, &C -- Use of SETC dup factor to * 00066000
71 * produce SETC string longer than 8, MNOTE in open code * 00067000
72 ***** 00068000
74 &la8 seta 1'a8 00070000
F 75 &ta8 setc t'a8 00071000
76 mnote *, 'Length of A8 = &LA8, Type of A8 = &TA8' 00072000
G **,Length of A8 = 2, Type of A8 = L 00072000
78 &a seta 2 00074000
79 &c setc (&a+3)'STRING,' 00075000
H 80 mnote *, '&&C has value = &c' 00076000
**,&C has value = STRING,STRING,STRING,STRING,STRING,STRING, 00076000
82 ***** 00078000
I 83 * Examples of 4 byte self-defined terms, unary + and - * 00079000
84 ***** 00080000
86 dc a(2147483647,C'ABCD',X'ffffffff') 00082000
000058 7FFFFFFFC1C2C3C4
000060 FFFFFFFF
000064 181D
FFFE8 87 lr -1+2,16+-3 00083000
89 X equ 4*-6 00085000
```

---

- F** Set symbols &LA8 and &TA8 have not been previously declared in LCL or GBL statements. Therefore, they default to local variable symbols as follows: &LA8 is an LCLA SET symbol because it appears in the name field of a SETA; &TA8 is an LCLC SET symbol because it is first used in a SETC.
- G** MNOTES can appear in open code. As such, they have all properties of MNOTES inside macros, including substitution.
- H** A SETC expression can have a duplication factor. The SETA expression must be enclosed in parentheses and immediately precede the character string, the substring notation, or the type attribute reference.
- I** Statements 86 through 89 show 4-byte self-defining values and unary + and -. The value of X appears later in a literal address constant (see statement 296).



```

BIGNAME Insert Programmer Macro in Source Stream now
Active Usings: a,R8
Loc Object Code Addr1 Addr2 Stmt Source Statement HLASM R6.0 2008/07/11 17.48
91 ***** 00087000
92 * Mixed keywords and positional parameters, extended AGO and AIF * 00088000
93 * statements, declaration and use of subscripted SET symbols, * 00089000
94 * Use of created SET symbols, extended SET statements * 00090000
95 ***** 00091000
J 97 macro 00093000
98 demo &p1,&key1=A,&p2,&key2=1,&p3,&key3=3,&p4 00094000
K 99 &loc(1) setc '2','3' &LOC is dimensioned LCLC by default 00095000
100 gblc &xa(5),&xb(20),&xc(1) 00096000
101 aif ('&system_id'(1,3) eq 'VSE').vse 00097000
L 102 &p1 &syslist(4),&syslist(5),&syslist(6),mf=E 00098000
103 ago .notvse 00099000
104 .vse anop Use VSE WRITE macro parameters 00100000
105 &p1 &syslist(4),SQ,&syslist(6) 00101000
106 .notvse anop 00102000
107 &n seta 1 00103000
M 108 ago (&key2).mnote1,.mnote2,.mnote3 00104000
109 &n seta 2 00105000
110 mnote *,'&&KEY2 not 1,2, or 3---Use &&KEY3 in place of it' 00106000
N 111 aif (&key3 eq 1).mnote1, 00107000
(&key3 eq 2).mnote2,(&key3 eq 3).mnote3 00108000
112 mnote *,'Both &&KEY2 and &&KEY3 fail to qualify' 00109000
113 ago .common 00110000
114 .mnote1 mnote *,'&&KEY&LOC(&N) = 1' 00111000
115 ago .common 00112000
116 .mnote2 mnote *,'&&KEY&LOC(&N) = 2' 00113000
117 ago .common 00114000
118 .mnote3 mnote *,'&&KEY&LOC(&N) = 3' 00115000
119 .common 1 5,8(,10) Note that opcodes, operands & comments 00116000
120 &xb(2) sr 9,10 on MODEL statements 00117000
O 121 &(x&key1)(2) lm 12,13,=a(a5,x) are kept in place unless displaced 00118000
122 &p2 st 7,&p3 as a result of substitution 00119000
123 mend 00120000
125 ***** DEMO MACRO instruction (call) 00122000
P 127 gblc &xa(1),&xb(2),&xc(3) 00124000
128 &xa(1) setc 'A','MISSISSIPPI' 00125000
129 &xb(1) setc 'B','SUSQUEHANNA' 00126000
130 &xc(1) setc 'C','PENNSYLVANIA' 00127000
Q 131 demo key3=2,write,reallylongsymbol, 000128000
a8+8*(b5-constant-7)(3),key1=C,(6),SF, 000129000
(8),key2=7 00130000
000066 1816 134+ LR 1,6 LOAD DECB ADDRESS 03-IHBRD
000068 9220 1005 00005 135+ MVI 5(1),X'20' SET TYPE FIELD 03-IHBRD
00006C 5081 0008 00008 136+ ST 8,8(1,0) STORE DCB ADDRESS 03-IHBRD
000070 58F1 0008 00008 137+ L 15,8(1,0) LOAD DCB ADDRESS 03-IHBRD
000074 58F0 F030 00030 138+ L 15,48(0,15) LOAD RDWR ROUTINE ADDR 03-IHBRD
000078 05EF 139+ BALR 14,15 LINK TO RDWR ROUTINE 03-IHBRD
140+*,&KEY2 not 1,2, or 3---Use &KEY3 in place of it 01-00110
141+*,&KEY3 = 2 01-00116
00007A 5850 A008 00008 142+ 1 5,8(,10) Note that opcodes, operands & comments 01-00119
00007E 1B9A R 143+SUSQUEHANNA sr 9,10 on MODEL statements 01-00120
000080 98CD 8090 00090 144+PENNSYLVANIA lm 12,13,=a(a5,x) are kept in place unless displaced 01-00121
BIGNAME Insert Programmer Macro in Source Stream now Page 7
Active Usings: a,R8
Loc Object Code Addr1 Addr2 Stmt Source Statement HLASM R6.0 2008/07/11 17.48
000084 5073 8098 00098 145+reallylongsymbol st 7,a8+8*(b5-constant-7)(3) X01-00122
+ as a result of substitution

```

**J** The macro DEMO is defined after the start of the assembly. Macros can be defined at any point and, having been defined, expanded, or both, can be redefined. The parameters on the prototype are a mixture of keywords and positional operands. &SYSLIST may be used. The positional parameters are identified and numbered 1, 2, 3 from left to right; keywords are skipped over in numbering positional parameters.

**K** Statement 99 shows the extended SET feature (as well as implicit declaration of &LOC(1) as an LCLC). Both &LOC(1) and &LOC(2) are assigned values. One SETA, SETB, or SETC statement can then do the work of many.

**L** Statement 102 is a model statement with a symbolic parameter in its operation field. This statement is edited as if it is a macro call; at this time, each operand is denoted as positional or keyword. At macro call time, you cannot reverse this decision. Even though it's treated as a macro, it is still expanded as a machine or assembler operation.

**M** Statement 108 shows the computed AGO statement. Control passes to

.MNOTE1 if &KEY2 is 1, to .MNOTE2 if &KEY2 is 2, to .MNOTE3 if &KEY2 is 3, or otherwise it falls through to the model statement at 109.

**N** Statement 111 shows the extended AIF facility. This statement is written in the alternative format. The logical expressions are examined from left to right. Control passes to the sequence symbol corresponding to the first true expression encountered, or else falls through to the next model statement.

**O** Statement 121 contains a subscripted created SET symbol in the name field. The created SET symbol has the form  $\&(e)$ , where  $e$  is an expression made up of character strings, variable symbols, or both. When the symbol is encountered during macro generation, the assembler evaluates the expression  $e$ . The operation code DEMO is used as a macro instruction in statement 131, and &KEY1 is given the value C. The  $e$  in this case is  $X\&KEY1$ , which results in the value XC. Thus the name field in statement 121,  $\&(x\&key1)(2)$ , becomes  $\&XC(2)$ . Statement 130 assigns the value C to  $\&XC(1)$ , and the value TRANSYLVANIA to  $\&XC(2)$ . The model statement (121) is generated at statement 144; the name field contains TRANSYLVANIA. The sequence field of statement 144, shows that this statement is a level 01 expansion of a macro, and the corresponding model statement is statement number 121.

You can use created SET symbols wherever regular SET symbols are used; for example: in declarations, name fields, operands of SET statements, model statements. Likewise, they are subject to all the restrictions of regular SET symbols.

**P** In statements 127 and 128,  $\&XA$  is declared as a subscripted global SETC variable with a subscript of 1 and in the next statement, which is an extended SET statement, we store the value MISSISSIPPI into  $\&XA(2)$ . The assembler allows up to 2,147,483,647 array values in a subscripted global SETC symbol.

**Q** Statement 131 is the macro instruction DEMO.  $\&P1$  has the value WRITE. Therefore, the model statement at statement 102 becomes an inner macro instruction, WRITE, producing the code at statements 134–139. The sequence field of these statements contains 03-IHBRD, indicating that they are generated by a level 03 macro (DEMO is 01, WRITE is 02) named IHBRDWRS. It is an inner macro called by WRITE.

**R** Statements 144 and 145 contain some ordinary symbols longer than 8 characters. The limit for ordinary symbols, operation codes (for programmer and library macros and operation codes defined through OPSYN), variable symbols, and sequence symbols, is 63 characters (including the  $\&$  and  $.$  in the latter two instances, respectively).

```

BIGNAME Insert Programmer Macro in Source Stream now
Active Usings: a,R8
Loc Object Code Addr1 Addr2 Stmt Source Statement HLASM R6.0 2008/07/11 17.48
147 ***** 00132000
148 * Copy 'NOTE' macro in from maclib, rename it 'MARK', call it under * 00133000
149 * its ALIAS -- in expansion of MARK, notice reference back to * 00134000
150 * definition statements in 'columns' 76-80 of expansion * 00135000
151 ***** 00136000
S 153 copy note 00138000
154= MACRO 00010000
155=&NAME NOTE &DCB,&DUMMY=,&TYPE=REL 00020000
156=.* $MAC(NOTE): 00030000
157=.* 5665-XA2 00032000
158=.* CONTAINS RESTRICTED MATERIALS OF IBM 00034000
159=.* (C) COPYRIGHT IBM CORP. 1984 00036000
160=.* LICENSED MATERIALS - PROPERTY OF IBM 00038000
161=.* REFER TO COPYRIGHT INSTRUCTIONS 00040000
162=.* FORM NUMBER G120-2083. 00042000
163=.* STATUS = MVS/XA DFP RELEASE 1.2 @H1 00044000
164=.* 00046990
165=.* CHANGE ACTIVITY = 00120000
166=.* 00130000
167=.* $H1=3480,JDP1111,,STLPKH: 3480 SUPPORT * 00140000
168=.* 00150000
169= AIF ('&DCB' EQ '').ERR 00160000
170=&NAME IHBINRA &DCB 00170000
171= AIF ('&TYPE' NE 'REL').NOTREL @H1A 00180000
172= L 15,84(0,1) LOAD NOTE RTN ADDRESS 00190000
173= BALR 14,15 LINK TO NOTE ROUTINE 00200000
174= MEXIT 00210000
175=.NOTREL AIF ('&TYPE' NE 'ABS').ERR1 @H1A 00220000
176= SLR 0,0 INDICATES NOTE MACRO @H1A 00230000
177= LA 15,32 ROUTER CODE @H1A 00240000
178= SVC 109 SUPERVISOR CALL @H1A 00250000
179= MEXIT @H1A 00260000
180=.ERR1 MNOTE 8,'INVALID PARAMETER FOR TYPE' @H1A 00270000
181= MEXIT @H1A 00280000
182=.ERR IHBEMAC 6 00290000
183= MEND 00300000
T 186 mark opsyn note Comments of generated statements occupy same 00141000
187 mark (6) 'COLUMNS' as those in MODEL statements 00142000
000088 1816 189+ LR 1,6 LOAD PARAMETER REG 1 02-IHBIN
00008A 58F0 1054 190+ L 15,84(0,1) LOAD NOTE RTN ADDRESS 01-00172
00008E 05EF 191+ BALR 14,15 LINK TO NOTE ROUTINE 01-00173
193 ***** 00144000
194 deeces loctr Switch to alternate location counter 00145000
0000B0 000AC 000DE 195 b5 ccw X'0b',b5,0,80 00146000
0000B0 0B0000B000000050 197 ***** 00148000
198 * Display of &SYSTIME, &SYSDATE, &SYSARM and &SYSLOC * 00149000
199 ***** 00150000
201 print nodata 00152000
U 202 dc c'TIME = &systime, DATE = &systdate, PARM = &sysparm' 00153000
BIGNAME Insert Programmer Macro in Source Stream now
Active Usings: a,R8
Loc Object Code Addr1 Addr2 Stmt Source Statement HLASM R6.0 2008/07/11 17.48
0000B8 E3C9D4C5407E40F1 + dc c'TIME = 17.22, DATE = 06/09/04, PARM = ' 00153000
204 macro 00155000
205 locate 00156000
V 206 &sysect csect Display of current control section 00157000
207 &sysloc loctr and location counter 00158000
208 mend 00159000
210 locate 00161000
0000DE 000AC 000DE 211+a csect Display of current control section 01-00206
0000DE 000AC 000DE 212+deeces loctr and location counter 01-00207
000090 00000 000DE 213 a loctr 00162000

```

**S** Library macros can be inserted into the source stream as programmer macros by use of a COPY statement. The result (statements 154 to 183) is treated as a source-stream macro definition. When a library macro is brought in and expanded by use of a macro instruction, the assembler (1) looks the macro up by its member-name and (2) verifies that this same name is used in the operation field of the prototype statement. Therefore, for example, DCB has to be cataloged as DCB. However, as COPY code, the member name bears no relationship to any of the statements in the member. Thus, several variations of a given macro could be stored as a library under separate names, then copied in at various places in a single assembly as needed. (High Level Assembler allows you to define and redefine a macro any number of times).

**T** In statement 186, MARK is made a synonym for NOTE. To identify the NOTE macro as a defined instruction mnemonic, it has to be used as either a system macro call (that is, from a macro library), or a programmer macro

## Sample program

definition, before its use in the operand field of an OPSYN statement. The COPY code at statements 154 through 183 is a programmer macro definition. The macro instruction at statement 187 is MARK. You can use MARK and NOTE interchangeably. If required, you could remove NOTE as a macro definition in the following way:

```
MARK      OPSYN      NOTE
NOTE      OPSYN      ,
```

You could then refer to the macro only as MARK.

**U** Statement 202 demonstrates &SYSTIME, &SYSDATE, and &SYSPARM. The values for the first two are the same as in the heading line. The value for &SYSPARM is the value passed in the PARM field of the EXEC statement, or the default value assigned to &SYSPARM when High Level Assembler is installed.

**V** System variable symbols &SYSLOC and &SYSECT are displayed at statements 211 and 212. The sequence field indicates that the model statements are statements 206 and 207.

---

BIGNAME Ordinary, Labeled and Dependent USING Instructions										Page 10
Active Usings: a,R8										
Loc	Object Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0 2008/07/11 17.48				
000000		00000	00814	215	*****	00164000				
000000				216	pd2 com	00166000				
0007D0	1867			217	ds 500f	00167000				
				218	lr 6,7	00169000				
				220	*****	00170000				
				221	* Use of ordinary, labeled and dependent USING Instructions	* 00170000				
				222	*****	00171000				
		R:C	007D2	224	using *,12	00173000				
0007D2	4110 C022		007F4	225	la 1,area1	00174000				
0007D6	4120 C032		00804	226	la 2,area2	00175000				
		R:1	00000	227	using first,1	Ordinary USING	00176000			
		R:2	00000	228	lab using first,2	Labeled USING	00177000			
		1	008 00000 00008	229	using second,first2	Dependent USING	00178000			
		2	008 00000 00008	230	labdep using third,lab.first2	Labeled dependent USING	00179000			
0007DA	D207 1000 8098 00000 00098			231	mvc first1,=c18'1st'	Uses ordinary USING	00180000			
0007E0	D207 2000 8098 00000 00098			232	mvc lab.first1,=c18'1st'	Uses labeled USING	00181000			
0007E6	D203 1008 80A0 00000 000A0			233	mvc second1,=c14'2nd'	Uses dependent USING	00182000			
0007EC	D201 2008 80A4 00000 000A4			234	mvc labdep.third1,=c12'3d'	Uses labeled dependent USING	00183000			
0007F4				235	area1 ds 0f	First data area	00184000			
0007F4				236	area1a ds c18		00185000			
0007FC				237	area1b ds c18		00186000			
000804				238	area2 ds 0f	Second data area	00187000			
000804				239	area2a ds c18		00188000			
00080C				240	area2b ds c18		00189000			
000000		00000	00010	241	first dsect	First dsect	00190000			
000000				242	first1 ds c18		00191000			
000008				243	first2 ds c18		00192000			
000000		00000	00008	244	second dsect	Second dsect	00193000			
000000				245	second1 ds c14		00194000			
000004				246	second2 ds c14		00195000			
000000		00000	000EC	247	third dsect	Third dsect	00196000			
000000				248	third1 ds c12		00197000			
000002				249	third2 ds c12		00198000			

---

**W** Illustration of named COMMON. You can establish addressability for a named COMMON section with:

USING section-name,register

You can address data in a blank COMMON section by labeling a statement within the section *after* the COMMON statement.

**X** In statement 227, an ordinary USING is established for AREA1 using the DSECT FIRST. When the fields within DSECT FIRST are referenced using symbols with the “first” qualifier, register 1 is used to resolve the address as in statement 231.

In statement 228, a labeled USING is established for AREA2 using the DSECT FIRST. Register 2 is used to resolve the address for qualified symbols within AREA2 when referred to using the qualifier “second” as in statement 232.

In statement 229, a dependent USING is established at the field FIRST2 using the DSECT SECOND. The corresponding ordinary USING for field FIRST2 is the USING on statement 227. It uses register 1 to resolve the address. The statement on line 233 specifies a field within DSECT SECOND and the assembler uses register 1 to resolve the address.

In statement 230, a labeled dependent USING is established at the field FIRST2 using the DSECT THIRD. The USING specifies the labeled USING LAB to resolve the address for field FIRST2. In statement 234, the labeled dependent USING is specified and register 2 is used to resolve the address of the field THIRD1.

---

```

BIGNAME  Predefined Absolute Symbols in SETA and SETC expressions                               Page 11
Active Usings: first,R1 second(X'FF8'),R1+X'8' a,R8 pd2+X'702',R12 lab.first,R2 labdep.third(X'FF8'),R2+X'8'
D-Loc  Object Code  Addr1 Addr2 Stmt  Source Statement                                     HLASM R6.0 2008/07/11 17.48
      251 *****
00064  255 hundred equ 100
      256 &divdnd seta 20
00032  Y 257 &percent seta &divdnd*100/40      Predefined symbol in SETA
      258 fifty equ 50
      Z 259 &longwd setc (hundred)'a'      Predefined symbol in SETC
      260      dc c'&longwd'
000004 8181818181818181      +      dc c'aaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaX00209000
00000C 8181818181818181      +      dc aaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaa
      261 &twowds setc (fifty)'a'.' '(hundred/2)'B'
      262      dc c'&twowds'
000068 8181818181818181      +      dc c'aaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaa BBX00211000
000070 8181818181818181      +      dc BBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBBB'

```

---

**Y** In statement 257, the SETA statement specifies a variable symbol (&DIVIDND) as well as other arithmetic terms.

**Z** In statement 259 the SETC statement specifies a predefined absolute symbol (HUNDRED) as the duplication factor.

## Sample program

```
BIGNAME Symbol Attribute Enhancements Page 12
Active Usings: first,R1 second(X'FF8'),R1+X'8' a,R8 pd2+X'7D2',R12 lab.first,R2 labdep.third(X'FF8'),R2+X'8'
D-Loc Object Code Addr1 Addr2 Stmt Source Statement HLAASM R6.0 2008/07/11 17.48

264 *****
265 * Symbol Attribute enhancements *
266 *****
0000CD C1C2C3 268 SYMBOL1 DC C'ABC' 00213000
0000D0 12345C 269 SYMBOL2 DC P'123.45' 00214000
270 &VAR1 SETC 'SYMBOL1' 00215000
271 &VAR2 SETC 'SYMBOL2' 00217000

0000D3 00 272 LA 1,=C'ABC' 00218000
0000D4 4110 80A6 273 LA 1,=P'123.45' 00219000
0000D8 4110 80A9 275 &TYPE SETC T'=C'ABC' 00220000
1 276 DC CL1'&TYPE' 00221000
277 DC CL1'C' 00222000
0000DC C3 + DC CL1(T'SYMBOL1) 00223000
0000DD C3 278 DC AL1(T'&VAR1) 00224000
0000DE C3 + DC AL1(T'SYMBOL1) 00225000
0000DF C3 279 DC AL1(T'=C'ABC') 00226000
2 280 &LEN SETA L'=C'ABC' 00227000
281 DC AL1(&LEN) 00228000
0000E0 03 + DC AL1(3) 00229000
0000E1 03 282 DC AL1(L'SYMBOL1) 00230000
283 DC AL1(L'&VAR1) 00231000
0000E2 03 + DC AL1(L'SYMBOL1) 00232000
0000E3 03 284 DC AL1(L'=C'ABC') 00233000
3 285 &INT SETA I'=P'123.45' 00234000
286 DC AL1(&INT) 00235000
0000E4 03 + DC AL1(3) 00236000
0000E5 03 287 DC AL1(I'SYMBOL2) 00237000
288 DC AL1(I'&VAR2) 00238000
0000E6 03 + DC AL1(I'SYMBOL2) 00239000
0000E7 03 289 DC AL1(I'=P'123.45') 00240000
4 290 &SCALE SETA S'=P'123.45' 00241000
291 DC AL1(&SCALE) 00242000
0000E8 02 + DC AL1(2) 00243000
0000E9 02 292 DC AL1(S'SYMBOL2) 00244000
293 DC AL1(S'&VAR2) 00245000
0000EA 02 + DC AL1(S'SYMBOL2) 00246000
0000EB 02 294 DC AL1(S'=P'123.45') 00247000
295 end 00248000

000090 00000044FFFFFFE8 5 296 =a(a5,x)
000098 F1A2A34040404040 297 =c18'1st'
0000A0 F2958440 298 =c14'2nd'
0000A4 F384 299 =c12'3d'
0000A6 C1C2C3 300 =C'ABC'
0000A9 12345C 301 =P'123.45'
```

- 1 The Type attribute (T) is allowed for ordinary symbols, SET symbols, and literals, in both conditional assembly instructions and machine or assembler instructions. It is allowed in both open code and macro definitions.
- 2 The Length attribute (L) is allowed for ordinary symbols, SET symbols, and literals, in both conditional assembly instructions and machine or assembler instructions. It is allowed in both open code and macro definitions.
- 3 The Integer attribute (I) is allowed for ordinary symbols, SET symbols, and literals, in both conditional assembly instructions and machine or assembler instructions. It is allowed in both open code and macro definitions.
- 4 The Scaling attribute (S) is allowed for ordinary symbols, SET symbols, and literals, in both conditional assembly instructions and machine or assembler instructions. It is allowed in both open code and macro definitions.
- 5 If there are literals outstanding when the END statement is encountered, they are assigned to the LOCTR now in effect for the first control section in the assembly. This may or may not put the literals at the end of the first control section. In this sample assembly, the first control section, A, has two LOCTRs: A and DEECEES. Because A is active (at statement 213), the literals are assembled there. You control placement of literal pools by

means of the LTORG statement. Note that X'FFFFFFE8' is used for the contents of A(X), statement 296. The symbol X was assigned the value (4\*-6) by an EQU in statement 89.

---

BIGNAME	Relocation Dictionary					Page 13
Pos.Id	Rel.Id	Address	Type	Action		HLASM R6.0 2008/07/11 17.48
00000001	00000001	00000090	A 4	+		
00000001	00000001	000000B1	A 3	+		

---

BIGNAME	Ordinary Symbol and Literal Cross Reference										Page 14
Symbol	Length	Value	Id	R	Type	Asm	Program	Defn	References		HLASM R6.0 2008/07/11 17.48
a	1	00000000	00000001		J			27	57	211 213	
area1	4	000007F4	00000002		F	F		235	225		
area2	4	00000804	00000002		F	F		238	226		
a5	2	00000044	00000001		I			63	67	296	
a8	2	000000B0	00000001		L			67	145M		
b5	8	000000B0	00000001		W			195	67	145M	195
constant	4	000000AC	00000001		F	F		56	54	145M	
decees	1	000000AC	00000001		J			55	194	212	
first	1	00000000	FFFFFFF		J			241	227U	228U	
first1	8	00000000	FFFFFFF		C	C		242	231M	232M	
first2	8	00000008	FFFFFFF		C	C		243	229U	230	
lab			00000002	A	U			228	230U	232	
labdep			00000002	A	U			230	234		
reallylongsymbol											
	4	00000084	00000001		I			145	42	47	
second	1	00000000	FFFFFFF		J			244	229U		
second1	4	00000000	FFFFFFF		C	C		245	233M		
SYMBOL1	3	000000CD	FFFFFFFD		C	C		268	277	278 282 283	
SYMBOL2	3	000000D0	FFFFFFFD		P	P		269	287	288 292 293	
third	1	00000000	FFFFFFFD		J			247	230U		
third1	2	00000000	FFFFFFFD		C	C		248	234M		
TRANSLYVANIA											
	4	00000080	00000001		I			144	42	47	
X	1	FFFFFFE8	00000001	A	U			89	296		
=a(a5,x)	4	00000090	00000001		A			296	144		
=c'ABC'	3	000000A6	00000001		C			300	272	279 284	
=c12'3d'	2	000000A4	00000001		C			299	234		
=c14'2nd'											
	4	000000A0	00000001		C			298	233		
=c18'1st'											
	8	00000098	00000001		C			297	231	232	
=P'123.45'											
	3	000000A9	00000001		P			301	273	289 294	

---



---

BIGNAME	Unreferenced Symbols Defined in CSECTs		Page 15
Defn	Symbol		HLASM R6.0 2008/07/11 17.48
65	a7		
143	SUSQUEHANNA		

---



---

BIGNAME	Macro and Copy Code Source Summary							Page 16
Con	Source			Volume	Members			HLASM R6.0 2008/07/11 17.48
	PRIMARY	INPUT			DEMO	LOCATE	NOTE	
L2	OSMACRO	MACLIB	S2	MNT190	IHBINNRA	IHBRDWS	NOTE	WRITE WTO

---



---

BIGNAME	Dsect Cross Reference				Page 17
Dsect	Length	Id	Defn		HLASM R6.0 2008/07/11 17.48
first	00000010	FFFFFFF	241		
second	00000008	FFFFFFF	244		
third	000000EC	FFFFFFFD	247		

---

## Sample program

---

BIGNAME		Using Map										Page 18	
HLASM R6.0 2008/07/11 17.48													
Stmt	Count	Location	Id	Action	Type	Value	Range	Id	Reg	Max	Disp	Last Label and Using Text	
28	00000000	00000001	USING	ORDINARY	00000000	00001000	00000001	8	000AC			273 *,8	
224	000007D2	00000002	USING	ORDINARY	000007D2	00001000	00000002	12	00032			226 *,12	
227	000007DA	00000002	USING	ORDINARY	00000000	00001000	FFFFFFF	1	00008			233 first,1	
228	000007DA	00000002	USING	LABELED	00000000	00001000	FFFFFFF	2	00008			232 lab.first,2	
229	000007DA	00000002	USING	DEPENDENT	+00000008	00000FF8	FFFFFFF	1				second,first2	
230	000007DA	00000002	USING	LAB+DEPND	+00000008	00000FF8	FFFFFFFD	2				labdep.third,lab.first2	

---

---

General Purpose Register Cross Reference															Page 19	
HLASM R6.0 2008/07/11 17.48																
Register	References (M=modified, B=branch, U=USING, D=DROP, N=index)															
0(0)	(no references identified)															
1(1)	63M	87M	134M	135	136N	137N	189M	190	225M	227U	272M	273M				
2(2)	63	226M	228U													
3(3)	145N															
4(4)	(no references identified)															
5(5)	54M	142M														
6(6)	134	189	218M													
7(7)	145	218														
8(8)	28U	136														
9(9)	143M															
10(A)	142	143														
11(B)	(no references identified)															
12(C)	144M	224U														
13(D)	87	144M														
14(E)	30B	139M	191M													
15(F)	29M	29	137M	138M	138	139B	190M	191B								

---

---

BIGNAME		Diagnostic Cross Reference and Assembler Summary										Page 20	
HLASM R6.0 2008/07/11 17.48													
No Statements Flagged in this Assembly													
HIGH LEVEL ASSEMBLER, 5696-234, RELEASE 5.0													
SYSTEM: CMS 15 JOBNAME: (NOJOB) STEPNAME: (NOSTEP) PROCSTEP: (NOPROC)													
Data Sets Allocated for this Assembly													
Con	DDname	Data Set Name								Volume	Member		
P1	SYSIN	ASMASAMP ASSEMBLE A1								DOGBOX			
L1	SYSLIB	BROOKES MACLIB A1								DOGBOX			
L2		OSMACRO MACLIB S2								MNT190			
L3		OSMACRO1 MACLIB S2								MNT190			
L4		DMSGPI MACLIB S2								MNT190			
	SYSLIN	ASMASAMP TEXT A1								DOGBOX			
	SYSPRINT	ASMASAMP LISTING A1								DOGBOX			
98138K allocated to Buffer Pool													
244 Primary Input Records Read 2217 Library Records Read													
0 ASMAOPT Records Read 485 Primary Print Records Written													
10 Object Records Written 0 ADATA Records Written													
Assembly Start Time: 17.22.51 Stop Time: 17.22.51 Processor Time: 00.00.00.0407													
Return Code 000													

---



---

## Appendix F. MHELP sample macro trace and dump

The macro trace and dump (MHELP) facility is a useful means of debugging macro definitions. MHELP can be used anywhere in the source program or in macro definitions. MHELP is processed during macro generation. It is completely dynamic; you can branch around the MHELP statements by using AIF or AGO statements. Therefore, you can control its use by symbolic parameters and SET symbols. MHELP options remain in effect until superseded by another MHELP statement.

Figure 61 on page 326 shows a sample program that uses five functions of MHELP. The macro dumps and traces in the listing are highlighted, for example **1A**. Most dumps refer to statement numbers. When you call a library macro, the macro name is used instead of the statement number in the identification-sequence field. To get the statement numbers, you should use the LIBMAC assembler option or the COPY statement to copy the library definition into the source program before the macro call.

### MHELP 1, Macro Call Trace

Item **1A** in Figure 61 on page 326 shows an outer macro call, **1B** in Figure 61 on page 326 an inner one. In each case, the amount of information given is short. This trace is given after successful entry into the macro; no dump is given if error conditions prevent an entry.

### MHELP 2, Macro Branch Trace

This trace provides a one-line trace for each AGO and true AIF branch within a programmer macro. In any such branch, the “branched from” statement number, the “branched to” statement number, and the macro name are included, see example **2A** in Figure 61 on page 326. The branch trace facility is suspended when library macros are expanded and MHELP 2 is in effect. To obtain a macro branch trace for such a macro, use the LIBMAC assembler option or insert a COPY “macro-name” statement in the source file at some point before the MHELP 2 statement of interest.

### MHELP 4, Macro AIF Dump

Items **4A**, **4B**, **4C**, **4D**, and **4E** in Figure 61 on page 326 are examples of these dumps. Each dump includes a complete set of unsubscripted SET symbols with values. This list covers all unsubscripted variable symbols that appear in the same field of a SET statement in the macro definition. Values of elements of dimensioned SET symbols are not displayed.

### MHELP 8, Macro Exit Dump

Items **8A** and **8B** in Figure 61 on page 326 are examples of these dumps. This option provides a dump of the same group of SET symbols as are included in the macro AIF dump when an MEXIT or MEND is encountered.

Local and global variable symbols are not displayed at any point unless they appear in the current macro explicitly as SET symbols.

### MHELP 16, Macro Entry Dump

This option provides a dump of the values of system variable symbols and symbolic parameters at the time the macro is called.

## MHELP sample macro trace and dump

If there are  $k$  keyword parameters, they are listed as KPARAM0001 through KPARAM000 $k$  in order of appearance on the prototype statement.

If there are  $p$  positional parameters, they are listed as PPARAM0001 through PPARAM000 $p$  in order of appearance in the macro instruction.

Item **16A** in Figure 61 has one keyword parameter (&OFFSET) and one positional parameter. In both the prototype (statement 4) and the macro instruction (statement 55), the positional parameter appears in the first operand field, the keyword in the second. A length appears between the NAME and VALUE fields. A length of NUL indicates the corresponding item is empty.

Item **16B** in Figure 61 shows an inner call containing zero keywords and two positional parameters.

### MHELP 64, Macro Hex Dump

This option, when used in conjunction with the Macro AIF dump, the Macro Exit dump, or the Macro Entry dump, dumps the parameter and SETC symbol values in EBCDIC and hexadecimal formats.

The hexadecimal dump precedes the EBCDIC dump, and dumps the full value of the symbol. System parameters are not dumped in hexadecimal.

### MHELP 128, MHELP Suppression

This option suppresses all the MHELP options that are active at the time.

### MHELP Control on &SYSNDX

The maximum value of the &SYSNDX system variable can be controlled by the MHELP instruction. The limit is set by specifying a number in the operand of the MHELP instruction, that is not one of the MHELP codes defined above, and is in the following number ranges:

- 256 to 65535
- Most numbers in the range 65792 to 9999999. Details for this number range are described in the *HLASM Language Reference*.

When the &SYSNDX limit is reached, message ASMA013S ACTR counter exceeded is issued, and the assembler, in effect, ignores all further macro calls. Refer to the *HLASM Language Reference* for further information.

---

Active Usings: None					PAGE 3	
Loc	Object Code	Addr1	Addr2	Stmnt	Source Statement	HLASM R6.0 2008/07/11 17.48
000000		00000	00000	1	csect	00246000
				2 *	copy lnsrc	00247000
				3	macro	00248000
				4 &name	lnsrc &arg,&offset=stnumb-stchain	00249000
				5	lcll &label	00250000
				6 &label	setc 'A&sysndx' Generate symbol	00251000
				7	aif (t'&name eq '0').skip	00252000
				8 &label	setc '&name' If MACRO call has label, use it	00253000
				9 .skip	anop instead of generated symbol	00254000
				10 &label	la 0,&offset Load reg. 0	00255000
				11	schi &arg,0(1) Search	00256000
				12	bc 1,&label If max reached, continue	00257000
				13	mend	00258000

---

Figure 61. Sample program using MHELP (Part 1 of 8)

Active Usings: None						Page	4
Loc	Object Code	Addr1	Addr2	Stmnt	Source Statement	HLASM R6.0	2008/07/11 17.48
15	*			copy	schl		00260000
16				macro			00261000
17	&nm			schl	&comp,&list		00262000
18				lcla	&cnt		00263000
19				lcll	&cmpadr		00264000
20	&cnt			seta	1		00265000
21	&nm			stm	1,15,4(13)		00266000
22	.test			anop			00267000
23	&cmpadr			setc	'&cmpadr'.'&comp'(&cnt,1)		00268000
24				aif	('&comp'(&cnt,1) eq '(').lpar		00269000
25	&cnt			seta	&cnt+1		00270000
26				aif	(&cnt lt k'&comp').test		00271000
27	.nolnth			anop			00272000
28				la	3,&comp Comparand		00273000
29				ago	.contin		00274000
30	.lpar			aif	('&comp'(&cnt+1,1) eq ',').finish		00275000
31	&cnt			seta	&cnt+1		00276000
32				aif	(&cnt lt k'&comp').lpar		00277000
33				ago	.nolnth		00278000
34	.finish			anop			00279000
35	&cmpadr			setc	'&cmpadr'.'&comp'(&cnt+2,k'&comp-&cnt)		00280000
36				la	3,&cmpadr Comparand sans length		00281000
37	.contin			anop			00282000
38				la	1,&list List header		00283000
39				mvc	&comp,0(0) Dummy move to get comp length		00284000
40				org	*-6 Change MVC to MVI		00285000
41				dc	x'92' MVI Opcode		00286000
42				org	*+1 Preserve length as immed opnd		00287000
43				dc	x'd000' Result is MVI 0(13),L		00288000
44				l	15,v(schl)		00289000
45				balr	14,15		00290000
46				lm	1,15,4(13)		00291000
47				mexit			00292000
48				mend			00293000

Figure 61. Sample program using MHELP (Part 2 of 8)

## MHELP sample macro trace and dump

Active Usings: None						Page	5
Loc	Object Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11 17.48
000000		00000	00048	50	test csect		00295000
000000	05C0			51	balr 12,0		00296000
	R	00002		52	using *,12		00297000
				54	mhelp b'11111'		00299000
				55	lnsrch listline,offset=listline-listnext		00300000
<b>1A</b>		++//MHELP CALL TO MACRO LNSRCH DEPTH=001 SYSNDX=0000001 STMT=00055					
<b>16A</b>		//MHELP ENTRY TO LNSRCH MODEL STMT=00000 DEPTH=001 SYSNDX=0000001 KWCNT=001					
		////SYSTEM PARAMETERS:					
		//SYSVAR NAME LNTH VALUE (56 CHARS/LINE)					
		//SYSNDX 004 0001					
		//SYSECT 004 test					
		//SYSLOC 004 test					
		//SYSTIME 005 17.48					
		//SYSDATE 008 07/11/08					
		//SYSASM 020 HIGH LEVEL ASSEMBLER					
		//SYSVER 005 1.6.0					
		//SYSDATC 008 20080711					
		//SYSJOB 007 (NOJOB)					
		//SYSSTEP 008 (NOSTEP)					
		//SYSSTYP 005 CSECT					
		//SYSSTMT 008 00000056					
		//SYSCLOCK 026 2008-07-11 17:48:42.914829					
		//SYSNST 001 1					
		//SYSSEQF 008 00300000					
		//SYSOPT_DBCS 001 0					
		//SYSOPT_OPTABLE 003 UNI					
		//SYSOPT_RENT 001 0					
		//SYSOPT_XOBJECT 001 0					
		//SYSTEM_ID 006 CMS 13					
		//SYSIN_DSN 020 ASMASAMP ASSEMBLE A1					
		//SYSIN_MEMBER NUL					
		//SYSIN_VOLUME 005 ADISK					
		//SYSLIB_DSN 020 ASMASAMP ASSEMBLE A1					
		//SYSLIB_MEMBER NUL					
		//SYSLIB_VOLUME 005 ADISK					
		//SYSPRINT_DSN 020 ASMASAMP LISTING A1					
		//SYSPRINT_MEMBER NUL					
		//SYSPRINT_VOLUME 005 ADISK					
		//SYSTEM_DSN NUL					
		//SYSTEM_MEMBER NUL					
		//SYSTEM_VOLUME NUL					
		//SYSPUNCH_DSN NUL					
		//SYSPUNCH_MEMBER NUL					
		//SYSPUNCH_VOLUME NUL					
		//SYSLIN_DSN 020 ASMASAMP TEXT A1					
		//SYSLIN_MEMBER NUL					
		//SYSLIN_VOLUME 005 ADISK					
		//SYSADATA_DSN NUL					
		//SYSADATA_MEMBER NUL					

Figure 61. Sample program using MHELP (Part 3 of 8)

Active Usings: test+X'2',R12

Page 6

Loc Object Code Addr1 Addr2 Stmt Source Statement HLASM R6.0 2008/07/11 17.48

```

//SYSADATA VOLUME NUL
//SYSPARM NUL
//SYSM_SEV 003 000
//SYSM_HSEV 003 000
////NAME; KEYWORD PARAMETERS; POSITIONAL PARAMETERS:
//PARAMETER LNTH VALUE (54 CHARS/LINE)
//NAME NUL
//KPARM0001 017 listline-listnext
//PPARM0001 008 listline

4A //MHELP AIF IN LNSRCH MODEL STMT=00007 DEPTH=001 SYSNDX=0000001 KWCNT=001
////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//
//0001 LCLC LABEL LNTH= 005
// VAL=A0001

2A ++//MHELP BRANCH FROM STMT 00007 TO STMT 00009 IN MACRO LNSRCH

000002 4100 0002 00002 56+A0001 1a 0,listline-listnext Load reg. 0 01-00010

18 ++//MHELP CALL TO MACRO SCHI DEPTH=002 SYSNDX=0000002 STMT=00011

16B //MHELP ENTRY TO SCHI MODEL STMT=00000 DEPTH=002 SYSNDX=0000002 KWCNT=000
////SYSTEM PARAMETERS:
//SYSVAR NAME LNTH VALUE (56 CHARS/LINE)
//SYSNDX 004 0002
//SYSECT 004 test
//SYSLOC 004 test
//SYSTIME 005 06.48
//SYSDATE 008 02/02/00
//SYSASM 020 HIGH LEVEL ASSEMBLER
//SYSVER 005 1.4.0
//SYSDATC 008 20000202
//SYSJOB 007 (NOJOB)
//SYSSTEP 008 (NOSTEP)
//SYSSTYP 005 CSECT
//SYSSTMT 008 00000058
//SYSCLOCK 026 2000-02-02 06:48:42.915979
//SYSNEST 001 2
//SYSSEQF 008 00300000
//SYSOPT_DBCS 001 0
//SYSOPT_OPTABLE 003 UNI
//SYSOPT_RENT 001 0
//SYSOPT_XOBJECT 001 0
//SYSTEM_ID 006 CMS 13
//SYSIN_DSN 020 ASMASAMP ASSEMBLE A1
//SYSIN_MEMBER NUL
//SYSIN_VOLUME 005 ADISK
//SYSLIB_DSN 020 ASMASAMP ASSEMBLE A1
//SYSLIB_MEMBER NUL
//SYSLIB_VOLUME 005 ADISK
//SYSPRINT_DSN 020 ASMASAMP LISTING A1
//SYSPRINT_MEMBER NUL

```

Figure 61. Sample program using MHELP (Part 4 of 8)

## MHELP sample macro trace and dump

Active Usings: test+X'2',R12

Page 7

Loc	Object Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11 17.48
					//SYSPRINT_VOLUME 005 ADISK		
					//SYSTEM_DSN NUL		
					//SYSTEM_MEMBER NUL		
					//SYSTEM_VOLUME NUL		
					//SYSPUNCH_DSN NUL		
					//SYSPUNCH_MEMBER NUL		
					//SYSPUNCH_VOLUME NUL		
					//SYSLIN_DSN 020 ASMASAMP TEXT A1		
					//SYSLIN_MEMBER NUL		
					//SYSLIN_VOLUME 005 ADISK		
					//SYSADATA_DSN NUL		
					//SYSADATA_MEMBER NUL		
					//SYSADATA_VOLUME NUL		
					//SYSPARM NUL		
					//SYSM_SEV 003 000		
					//SYSM_HSEV 003 000		
					///NAME; KEYWORD PARAMETERS; POSITIONAL PARAMETERS:		
					//PARAMETER LNTH VALUE (54 CHARS/LINE)		
					//NAME NUL		
					//PPARM0001 008 listline		
					//PPARM0002 004 0(1)		
000006	901F D004		00004	58+	stm 1,15,4(13)		02-00021
	<b>4B</b>				//MHELP AIF IN SCHI MODEL STMT=00024 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT VAL= 0000000001		
					//0002 LCLC CMPADR LNTH= 001		
					// VAL=1		
	<b>4C</b>				//MHELP AIF IN SCHI MODEL STMT=00026 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT VAL= 0000000002		
					//0002 LCLC CMPADR LNTH= 001		
					// VAL=1		
					++//MHELP BRANCH FROM STMT 00026 TO STMT 00022 IN MACRO SCHI		
	<b>4D</b>				//MHELP AIF IN SCHI MODEL STMT=00024 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT VAL= 0000000002		
					//0002 LCLC CMPADR LNTH= 002		
					// VAL=1i		
	<b>4E</b>				//MHELP AIF IN SCHI MODEL STMT=00026 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT VAL= 0000000003		
					//0002 LCLC CMPADR LNTH= 002		
					// VAL=1i		

Figure 61. Sample program using MHELP (Part 5 of 8)

Page 8

Active Usings: test+X'2',R12  
 Loc Object Code Addr1 Addr2 Stmt Source Statement HLASM R6.0 2008/07/11 17.48

```

++//MHELP BRANCH FROM STMT 00026 TO STMT 00022 IN MACRO SCHI

//MHELP AIF IN SCHI MODEL STMT=00024 DEPTH=002 SYSNDX=0000002 KWCNT=000
////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//
//0001 LCLA CNT VAL= 0000000003
//0002 LCLC CMPADR LNTH= 003
// VAL=1is

//MHELP AIF IN SCHI MODEL STMT=00026 DEPTH=002 SYSNDX=0000002 KWCNT=000
////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//
//0001 LCLA CNT VAL= 0000000004
//0002 LCLC CMPADR LNTH= 003
// VAL=1is

++//MHELP BRANCH FROM STMT 00026 TO STMT 00022 IN MACRO SCHI

//MHELP AIF IN SCHI MODEL STMT=00024 DEPTH=002 SYSNDX=0000002 KWCNT=000
////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//
//0001 LCLA CNT VAL= 0000000004
//0002 LCLC CMPADR LNTH= 004
// VAL=1ist

//MHELP AIF IN SCHI MODEL STMT=00026 DEPTH=002 SYSNDX=0000002 KWCNT=000
////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//
//0001 LCLA CNT VAL= 0000000005
//0002 LCLC CMPADR LNTH= 004
// VAL=1ist

++//MHELP BRANCH FROM STMT 00026 TO STMT 00022 IN MACRO SCHI

//MHELP AIF IN SCHI MODEL STMT=00024 DEPTH=002 SYSNDX=0000002 KWCNT=000
////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//
//0001 LCLA CNT VAL= 0000000005
//0002 LCLC CMPADR LNTH= 005
// VAL=1ist1

//MHELP AIF IN SCHI MODEL STMT=00026 DEPTH=002 SYSNDX=0000002 KWCNT=000
////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//
//0001 LCLA CNT VAL= 0000000006
//0002 LCLC CMPADR LNTH= 005
// VAL=1ist1

++//MHELP BRANCH FROM STMT 00026 TO STMT 00022 IN MACRO SCHI

//MHELP AIF IN SCHI MODEL STMT=00024 DEPTH=002 SYSNDX=0000002 KWCNT=000

```

Figure 61. Sample program using MHELP (Part 6 of 8)

## MHELP sample macro trace and dump

Active Usings: test+X'2',R12						Page	9
Loc	Object Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11 17.48
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT	VAL=	0000000006
					//0002 LCLC CMPADR	LNTH=	006
					// VAL=listli		
					////MHELP AIF IN SCHI MODEL STMT=00026 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT	VAL=	0000000007
					//0002 LCLC CMPADR	LNTH=	006
					// VAL=listli		
					++//MHELP BRANCH FROM STMT 00026 TO STMT 00022 IN MACRO SCHI		
					////MHELP AIF IN SCHI MODEL STMT=00024 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT	VAL=	0000000007
					//0002 LCLC CMPADR	LNTH=	007
					// VAL=listlin		
					////MHELP AIF IN SCHI MODEL STMT=00026 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT	VAL=	0000000008
					//0002 LCLC CMPADR	LNTH=	007
					// VAL=listlin		
00000A	4130 C024		00026	59+	la 3,listline	Comparand	02-00028
					++//MHELP BRANCH FROM STMT 00029 TO STMT 00037 IN MACRO SCHI		
00000E	4111 0000		00000	60+	la 1,0(1)	List header	02-00038
000012	D202 C024 0000	00026	00000	61+	mvc listline,0(0)	Dummy move to get comp length	02-00039
000018		00018	00012	62+	org *-6	Change MVC to MVI	02-00040
000012	92			63+	dc x'92'	MVI Opcode	02-00041
000013		00013	00014	64+	org *+1	Preserve length as immed opnd	02-00042
000014	D000			65+	dc x'd000'	Result is MVI 0(13),L	02-00043
000016	58F0 C02E		00030	66+	l 15,=v(schi)		02-00044
00001A	05EF			67+	balr 14,15		02-00045
00001C	981F D004		00004	68+	lm 1,15,4(13)		02-00046
					8A //MHELP EXIT FROM SCHI MODEL STMT=00047 DEPTH=002 SYSNDX=0000002 KWCNT=000		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLA CNT	VAL=	0000000008
					//0002 LCLC CMPADR	LNTH=	007
					// VAL=listlin		
000020	4710 C000		00002	69+	bc 1,A0001	If max reached, continue	01-00012
					8B //MHELP EXIT FROM LNSRCH MODEL STMT=00013 DEPTH=001 SYSNDX=0000001 KWCNT=001		
					////SET SYMBOLS (SKIPPED NUMBERS MAY BE SEQUENCE SYMBOLS).//		
					//0001 LCLC LABEL	LNTH=	005
					// VAL=A0001		
					:		
					:		
Active Usings: test+X'2',R12						Page	10
Loc	Object Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11 17.48
000024				70	listnext ds h		00301000
000026				71	listline ds f13'0'		00302000
000030				72	ltorg		00303000
000030	00000000			73	=v(schi)		
					:		

Figure 61. Sample program using MHELP (Part 7 of 8)



---

New Floating-point Constants included for Verification						Page	11
Active Usings: test+X'2',R12							
Loc	Object Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11 17.48
				75	*****		00305000
				76	* New FP definitions included to verify correct release of HLASM *		00306000
				77	*****		00307000
000034	00000000						
000038	4093480000000000			78	BFP1 DC DB'1234'		00308000
000040	434D200000000000			79	HFP1 DC DH'1234'		00309000
000000				80	end test		00310000

---

Figure 61. Sample program using MHELP (Part 8 of 8)

## MHELP sample macro trace and dump

---

## Appendix G. High Level Assembler messages

High Level Assembler produces the following types of messages:

- Assembly error-diagnostic messages.
- Assembly abnormal-termination messages.
- ASMAHL command-error messages (CMS).

The following section describes the format and placement of messages issued by the assembler. “Assembly error diagnostic messages” on page 338, “Abnormal assembly termination messages” on page 380, and “ASMAHL Command Error Messages (CMS)” on page 385, list and describe each message.

**Note:** If you use the FLAG(*severity code*) assembler option, only error diagnostic messages with a severity of *severity code* or higher appear on the listing.

---

### Message code format

Assembly error diagnostic messages, and assembly abnormal termination messages, have the following message code format:

ASMA*nnns*

*nnn*     a three-character message number

*s*        severity indicator

The severity indicators, and the corresponding severity codes are:

**I—Informational**

(Severity code = 0)

This error does not affect the running of the program; rather, it is a coding inefficiency or other such condition that can be changed. The assembler has not detected any conditions affecting the correctness of the program.

**N—Notice**

(Severity code = 2)

This type of message brings your attention to a condition that you might wish to correct. The assembler has not detected any conditions affecting the correctness of the program; however, the output from the assembly might not be what you expect.

**W—Warning**

(Severity code = 4)

Although the statement in which the condition occurs is syntactically correct, it has the potential for causing an error when the program is run.

**E—Error**

(Severity code = 8)

The condition is definitely an error. However, the assembler has tried to correct the error, or has ignored the statement in error. The program probably will not run successfully.

**S—Severe**

(Severity code = 12)

## Message code format

The condition is a serious error. The assembler has either ignored the statement in error, or the machine instruction has been assembled to zero. It is not likely that the program will assemble as expected or that it will run.

**C—Critical** (Severity code = 16)

The condition is a critical error. It is not likely that the program will run successfully.

**U—Unrecoverable**  
(Severity code = 20)

The error condition is of such magnitude that the assembler could not continue.

ASMAHL command error messages have the following message code format:

ASMACMSnnne

where:

*nnn* Is a three-character message number

*e* Indicates the severity of an error. See 337.

**LANGUAGE Assembler Option:** Unless otherwise indicated, the text of ASMAHL command error messages is produced in the language specified on the LANGUAGE operand in the installation default options.

---

## Message descriptions

Each message entry for assembly error diagnostic messages and assembly abnormal termination messages has the following five sections:

- Message Number and Text
- Explanation of Message
- System Action
- Programmer Response
- Severity Code

Each message entry for ASMAHL command error messages has up to five of the following sections:

- Message Number and Text
- Explanation of Message
- Supplemental Information
- System Action
- Programmer Response

### Message Number and Text

Only the message number and the major fixed portion of the message text are included in the message description. Any abbreviations in actual message text are described under the message explanation section. Unused message numbers account for the gaps in the message number sequence. No messages are defined for numbers which are not included in this section (for example, ASMA222).

### Explanation of Message

For some messages there is more than one explanation, as different sections of the assembler can generate the same message. Several assembler termination messages have identical explanations.

### Supplemental Information

For ASMAHL command error messages, the supplemental information describes the possible contents of the variables in the message text.

### System Action

This section describes how the assembler handles statements with errors. Some actions include:

- A machine instruction assembles as all zeros.
- An assembler instruction is usually ignored; it is printed but has no effect on the assembly. Many assembler instructions, however, are partially processed or processed with a default value. For some instructions, the operands preceding the operand in error, or every operand except the operand in error, is processed. For example, if one of several operands on a DROP statement is a symbol that cannot be evaluated to a register number, only that operand is ignored. All the correctly-specified registers are processed correctly.
- For some assembler statements, especially macro prototype and conditional assembly statements, the operand or term in error is given a default value. Thus the statement assembles completely, but will probably cause incorrect results if the program is run.

For ASMAHL command error messages, this section describes the command return code and the status of the system after the error.

### Programmer Response

Many errors have specific or probable causes. In such a case, the Programmer Response section gives specific steps for fixing the error. Most messages, however, have too many possible causes to list (from keying errors to wrong use of the statement). The Programmer Response section for these error messages does not give specific directions. The cause of most such errors can be determined from the message text and the explanation.

### Severity Code

The level of severity code indicates how critical the error might be. The severity codes and their meanings are described in “Message code format” on page 335.

ASMAHL messages (those messages starting with ASMACMS) have a severity code letter of E. The associated return code is shown in the System Action for each message. An ASMAHL message that causes the assembly to terminate generates a return code greater than 20.

The severity code is used to determine the return code issued by the assembler when it returns control to the operating system. The IBM-supplied cataloged procedures (for z/OS) include a COND parameter on the linkage edit and run steps. The COND parameter prevents the running of these steps if the return code from the assembler is greater than 8. Thus errors with a severity code of S prevent the assembled program from linkage editing or running. Errors with a severity code of E, or lower, in the message do not prevent the assembled program from linkage editing or running.

---

### Assembly error diagnostic messages

High Level Assembler prints most error messages in the listing immediately following the statements in error. It also prints the total number of flagged statements and their statement numbers in the Diagnostic Cross Reference and Assembler Summary section of the assembler listing.

The messages do not follow the statement in error when:

- Errors are detected during editing of macro definitions read from a library. A message for such an error appears after the first call in the source program to that macro definition. You can, however, bring the macro definition into the source program with a COPY statement. The editing error messages will then be attached to the statements in error.
- Errors are detected by the lookahead function of the assembler. (For attribute references, lookahead processing scans statements after the one being assembled.). Messages for these errors appear after the statements in which they occur. The messages might also appear at the point at which lookahead was called.
- Errors are detected on conditional assembly statements during macro generation or MHELP testing. Such a message follows the most recently generated statement or MHELP output statement.

A typical error diagnostic message is:

```
** ASMA057E Undefined operation code - xxxxx
```

A copy of a segment of the statement in error, represented above by *xxxxx*, is inserted into many messages. Normally this segment begins at the bad character or term. For some errors, however, the segment might begin after the bad character or term. The segment might include part of the remarks field.

If a diagnostic message follows a statement generated by a macro definition, the following items might be appended to the error message:

- The number of the model statement in which the error occurred, or the first five characters of the macro name.
- The SET symbol, system variable, macro parameter, or value string associated with the error.

Messages may reference three types of macro parameter: the *name field* parameter, *keyword* parameters, and *positional* parameters. A reference to the name field parameter is indicated by the word "NAME" appended to the message. References to keyword and positional parameters (for which there may be multiple occurrences) are in the form "KPARAM<sub>nnnn</sub>" and "PPARM<sub>nnnn</sub>" respectively, where *nnnn* is the relative number of the parameter within the macro definition.

Figure 62 on page 339 shows an example of a macro with messages referencing each type of variable or parameter.

Loc	Object	Code	Addr1	Addr2	Stmt	Source Statement	HLASM R6.0	2008/07/11	17.48
					1	MACRO			00001000
					2	&z parms &kw1=a,&kw2=b,&kw3=c,&kw4=d,&kw5=e,&kw6=f,&pp1,&pp2			00002000
					3	&c SETC 'just a string'			00003000
					4	&ss SETA &c			00004000
					5	&sv SETA &sysasm			00005000
					6	&z1 SETA &z			00006000
					7	&k1 SETA &kw1			00007000
					8	&k5 SETA &kw5			00008000
					9	&n SETA n'&syslist			00009000
					10	&pn SETA &syslist(&n)			00010000
					11	&p2 SETA &pp2			00011000
					12	MEND			00012000
000000			00000	00000	13	default CSECT			00013000
					14	n parms pp1,pp2,kw5=z,pp3,kw1=y,pp4,pp5,pp6			00014000
ASMA102E	Arithmetic term is not					self-defining term; default=0 - 00004/C			
ASMA102E	Arithmetic term is not					self-defining term; default=0 - 00005/SYSASM			
ASMA102E	Arithmetic term is not					self-defining term; default=0 - 00006/NAME			
ASMA102E	Arithmetic term is not					self-defining term; default=0 - 00007/KPARAM00001			
ASMA102E	Arithmetic term is not					self-defining term; default=0 - 00008/KPARAM00005			
ASMA102E	Arithmetic term is not					self-defining term; default=0 - 00010/PPARM00006			
ASMA102E	Arithmetic term is not					self-defining term; default=0 - 00011/PPARM00002			
					15	END			00015000

Figure 62. Sample macro parameter messages

## Notes to Figure 62:

- 1** SET symbol, and related message
- 2** System variable symbol, and related message
- 3** The name field parameter, and related message
- 4** Keyword parameters, and related messages
- 5** Positional parameters, and related messages

If a diagnostic message follows a conditional assembly statement in the source program, the following items are appended to the error message:

- The word “OPENC”, meaning “open code”.
- The SET symbol, or value string, associated with the error.

Several messages might be issued for a single statement or even for a single error within a statement. This happens because each statement is usually evaluated on more than one level (for example, term level, expression level, and operand level) or by more than one phase of the assembler. Each level or phase can diagnose errors; therefore, most or all of the errors in the statement are flagged.

Occasionally, duplicate error messages might occur. This is a normal result of the error-detection process.

## Message not known

The following message might appear in a listing:

```
** ASMA000E Message not known - nnn
```

The statement preceding this message contains an error but the assembler routine that detected the error issued the number (*nnn*) of a nonexistent error message to the assembler’s message generation routine. If you can correct the error, this statement will assemble correctly. However, this message indicates an error in the error detection process of the assembler. Save the output and the source files from this assembly and report the problem to your IBM service representative.

## Messages

---

### ASMA001E Operation code not allowed to be generated - xxxxxxxx

**Explanation:** An attempt was made to produce a restricted operation code by variable symbol substitution. Restricted operation codes are:

ACTR	AGO	AGOB	AIF
AIFB	ANOP	AREAD	COPY
GBLA	GBLB	GBLC	ICTL
ISEQ	LCLA	LCLB	LCLC
MACRO	MEND	MEXIT	REPRO
SETA	SETAF	SETB	SETC
SETCF			

**System action:** The statement is ignored.

**Programmer response:** If you want a variable operation code, use AIF to branch to the correct unrestricted statement.

**Severity:** 8

---

### ASMA002S Generated statement too long; statement truncated - xxxxxxxx

**Explanation:** The statement generated by a macro definition is more than 3072 characters long.

**System action:** The statement is truncated; the leading 1728 characters are retained.

**Programmer response:** Shorten the statement.

**Severity:** 12

---

### ASMA003E Undeclared variable symbol; default=0, null, or type=U - xxxxxxxx

**Explanation:** A variable symbol in the operand field of the statement has not been declared (defined) in the name field of a SET statement, in the operand field of an LCL or GBL statement, or in a macro prototype statement.

**System action:** The variable symbol is given a default value as follows:

SETA = 0  
 SETB = 0  
 SETC = null (empty) string

If the assembler is unable to determine an appropriate type from the context of the symbol's use, a default type of SETC is assigned.

The type attribute (T') of the variable is given a default value of U (undefined).

**Programmer response:** Declare the variable *before* you use it as an operand.

**Severity:** 8

---

### ASMA004E Duplicate SET symbol declaration; first is retained - xxxxxxxx

**Explanation:** A SET symbol has been declared (defined) more than once. A SET symbol is declared when it is used in the name field of a SET statement, in the operand field of an LCL or GBL statement, or in a macro prototype statement.

**System action:** The value of the first declaration of the SET symbol is used.

**Programmer response:** Eliminate the incorrect declarations.

**Severity:** 8

---

### ASMA005S No storage for macro call; continue with open code

**Explanation:** An inner macro call could not be processed because no main storage was available.

**System action:** The assembly continues with the next open code statement.

**Programmer response:** Check whether the macro is recursive, and, if so, whether termination is provided for; correct the macro if necessary. If the macro is correct, allocate more main storage.

**Severity:** 12

---

### ASMA007S Previously defined sequence symbol - xxxxxxxx

**Explanation:** The sequence symbol in the name field has been used in the name field of a previous statement.

**System action:** The first definition of the sequence symbol is used; this definition is ignored.

**Programmer response:** Remove or change one of the sequence symbols.

**Severity:** 12

---

### ASMA008S Previously defined symbolic parameter - xxxxxxxx

**Explanation:** The xxxxxxxx symbol has been used to define two different symbolic parameters.

**System action:** When the parameter name (the variable symbol) is used inside the macro definition, it refers to the *first* definition of the parameter in the prototype. However, if the second parameter defined by the variable symbol is a positional parameter, the count of positional operands still increases by one. The second parameter can then be referred to only through use of &SYSLIST.



**Programmer response:** Change one of the parameter names to another variable symbol.

**Severity:** 12

---

### ASMA009S System variable symbol illegally re-defined

**Explanation:** A system variable symbol has been used in the name field of a macro prototype statement. The system variable symbols are:

---

&SYSADATA_DSN	&SYSNDX
&SYSADATA_MEMBER	&SYSNEST
&SYSADATA_VOLUME	&SYSOPT_DBCS
&SYSASM	&SYSOPT_OPTABLE
&SYSCLOCK	&SYSOPT_RENT
&SYSDATC	&SYSOPT_XOBJECT
&SYSDATE	&SYSPARM
&SYSECT	&SYSPRINT_DSN
&SYSIN_DSN	&SYSPRINT_MEMBER
&SYSIN_MEMBER	&SYSPRINT_VOLUME
&SYSIN_VOLUME	&SYSPUNCH_DSN
&SYSJOB	&SYSPUNCH_MEMBER
&SYSLIB_DSN	&SYSPUNCH_VOLUME
&SYSLIB_MEMBER	&SYSSEQF
&SYSLIB_VOLUME	&SYSSTEP
&SYSLIN_DSN	&SYSSTMT
&SYSLIN_MEMBER	&SYSSTYP
&SYSLIN_VOLUME	&SYSTEM_ID
&SYSLIST	&SYSTEM_DSN
&SYSLOC	&SYSTEM_MEMBER
&SYSM_HSEV	&SYSTEM_VOLUME
&SYSM_SEV	&SYSTIME
&SYSMAC	&SYSVER

---

**System action:** The name parameter is ignored. The name on a corresponding macro instruction is not generated.

**Programmer response:** Change the parameter to one that is not a system variable symbol.

**Severity:** 12

---

### ASMA010E Invalid use of symbol qualifier - xxxxxxxx

**Explanation:** One of the following has occurred:

- A symbol qualifier has been used to qualify a symbol in other than:
  - A machine instruction
  - The nominal value of an S-type address constant
  - The supporting address operand of a dependent USING statement
- A symbol qualifier is used to qualify a symbol that has an absolute value where a symbol that represents a relocatable address is required
- A symbol qualifier is used to qualify a symbol that is not within the range of the corresponding labeled USING statement

- A symbol qualifier is used to qualify an undefined symbol
- A symbol qualifier is used to qualify an incorrect symbol
- A period is used as the last character of a term, but the symbol preceding the period has not been defined in the name field of a labeled USING statement

A symbol qualifier can only be used in machine instructions, the nominal value of S-type address constants, or the second operand (supporting base address) of dependent USING instructions. A symbol qualifier can only be used to qualify symbols that are within the range of the corresponding labeled USING.

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored. If there is a further error in the statement, a message that describes the error is issued.

**Programmer response:** Correct the use of the symbol qualifier, or check the statement for the error indicated in the following message.

**Severity:** 8

---

### ASMA011E Inconsistent global declarations; first is retained - xxxxxxxx

**Explanation:** A global SET variable symbol has been defined in more than one macro definition or in a macro definition and in the source program, and the two definitions are inconsistent in type or dimension.

**System action:** The first definition encountered is retained.

**Programmer response:** Assign a new SET symbol or make the declaration compatible.

**Severity:** 8

---

### ASMA012S Undefined sequence symbol - xxxxxxxx; macro aborted

**Explanation:** A sequence symbol in the operand field is not defined; that is, it is not used in the name field of a model statement.

**System action:** Exit from the macro definition.

**Programmer response:** Define the sequence symbol or correct the reference to it.

**Severity:** 12

---

### ASMA013S ACTR counter exceeded - xxxxxxxx

**Explanation:** The conditional assembly loop counter (set by an ACTR statement) has been decremented to zero. The ACTR counter is decremented by one each time an AIF or AGO branch is processed successfully. The counter is halved for most errors encountered by

## Assembly error diagnostic messages

the macro editor phase of the assembler.

**System action:** Any macro expansion stops. If the ACTR statement is in the source program, the assembly stops.

**Programmer response:** Check for an AIF/AGO loop or another type of error. (You can use the MHELP facility, described in Chapter 6, “Diagnosing assembly errors,” on page 153 and Appendix F, “MHELP sample macro trace and dump,” on page 325, to trace macro definition logic.) If there is no error, increase the initial count on the ACTR instruction.

**Severity:** 12

---

### ASMA014E Irreducible qualified expression

**Explanation:** The statement cannot be resolved because two or more qualified symbols are used in a complex relocatable expression, or two or more qualified symbols with different symbol qualifiers are paired in an absolute expression.

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored.

**Programmer response:** Supply an absolute expression, or correct the qualified symbol in error.

**Severity:** 8

---

### ASMA015W Literal bounds exceeded

**Explanation:** The expression containing the reference to the literal:

- resolves to an address outside the bounds of the literal
- the length of the receiving field is longer than the length of the literal

This indicates a potential error.

**System action:** The instruction assembles as specified.

**Programmer response:** Change the expression to not exceed the bounds.

**Severity:** 4

---

### ASMA016W Literal used as the target of `xxxxx` instruction

**Explanation:** The target of instruction `xxxxx` is a literal. This indicates a potential error. `xxxxx` is output in uppercase.

**System action:** The instruction assembles as specified.

**Programmer response:** Specify the instruction target correctly. You can suppress this warning for an EX instruction by specifying the NOEXLITW suboption of the FLAG option.

**Severity:** 4

---

### ASMA017W Undefined keyword parameter; default to positional, including keyword - `xxxxxxx`

**Explanation:** A keyword parameter in a macro call is not defined in the corresponding macro prototype statement.

This message is also generated by a valid positional parameter that contains an equal sign.

**System action:** The keyword (including the equals sign and value) is used as a positional parameter.

**Programmer response:** Define the keyword in the prototype statement, or enclose the valid positional parameter in parentheses, or single quotation marks, and adjust the macro coding appropriately.

**Severity:** 4

---

### ASMA018S Duplicate keyword in macro call; last value is used - `xxxxxxx`

**Explanation:** A keyword operand occurs more than once in a macro call.

**System action:** The latest value assigned to the keyword is used.

**Programmer response:** Eliminate one of the keyword operands.

**Severity:** 12

---

### ASMA019W Length of EQUated symbol `xxxxxxx` undefined; default=1

**Explanation:** The value of the length attribute extracted for an EQUated symbol with an unspecified length has been set to the default: 1.

**System action:** The instruction assembles as specified.

**Programmer response:** Ensure that the length attribute of the symbol is defined.

**Severity:** 4

---

### ASMA020E Illegal GBL or LCL statement - `xxxxxxx`

**Explanation:** A global (GBL) or local (LCL) declaration statement does not have an operand.

**System action:** The statement is ignored.

**Programmer response:** Remove the statement or add an operand.

**Severity:** 8

---

### ASMA021E Illegal SET statement - `xxxxxxx`

**Explanation:** The operand of a SETB statement is not 0, 1, or a SETB expression enclosed in parentheses.

**System action:** The statement is ignored.

**Programmer response:** Correct the operand or delete the statement.

**Severity:** 8

---

### ASMA022I START value rounded up to required boundary

**Explanation:** The value specified in the operand field of the START instruction has been rounded up to the required boundary.

**System action:** The assembly continues.

**Programmer response:** To stop the message occurring, specify the required boundary for the value.

**Severity:** 0

---

### ASMA023E Symbolic parameter too long - xxxxxxxx

**Explanation:** A symbolic parameter in this statement is too long. It must not exceed 63 characters, including the initial ampersand.

**System action:** The symbolic parameter and any operand following it in this statement are ignored.

**Programmer response:** Make sure all symbolic parameters consist of an ampersand followed by 1 to 62 alphanumeric characters, the first of which is alphabetic.

**Severity:** 8

---

### ASMA024E Invalid variable symbol - xxxxxxxx

**Explanation:** One of these errors has occurred:

- A symbolic parameter or a SET symbol is not an ampersand followed by 1 to 62 alphanumeric characters, the first being alphabetic.
- A created SET symbol definition is not a valid SET symbol expression enclosed in parentheses.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid symbol or expression.

**Severity:** 8

---

### ASMA025S Invalid macro prototype operand - xxxxxxxx

**Explanation:** The format of the operand field of a macro prototype statement is not correct. For example, two parameters are not separated by a comma, or a parameter contains characters that are not permitted.

**System action:** The operand field of the prototype is ignored.

**Programmer response:** Supply a valid operand field.

**Severity:** 12

---

### ASMA026S Macro call operand too long; leading characters deleted - xxxxxxxx

**Explanation:** An operand of a macro instruction is more than the allowable length.

**System action:** The leading characters (for the allowable length) are deleted.

**Programmer response:** Split the operand into two or more operands.

**Severity:** 12

---

### ASMA027S Excessive number of operands

**Explanation:** One of the following has occurred:

- More than 32000 positional operands, keyword operands, or both have been explicitly defined in a macro prototype statement.
- There are more than 255 operands in a DC, DS, or DXD statement.

**System action:** The excess parameters are ignored.

**Programmer response:** For a DC, DS, or DXD statement, use more than one statement. For a macro prototype statement, delete the extra operands and use &SYSLIST to access the positional operands, or redesign the macro definition.

**Severity:** 12

---

### ASMA028E Invalid displacement

**Explanation:** One of the following has occurred:

- The displacement field of an explicit address is not an absolute value within the range 0 through 4095.
- The displacement field of an S-type address constant is not an absolute value within the range 0 through 4095.
- | • The displacement of a long-displacement instruction cannot be resolved to lie within the range from
- | -524288 to +524287.

**System action:** The statement or constant assembles as zero.

**Programmer response:** Correct the displacement or supply a correct USING statement containing an absolute first operand before this statement.

**Severity:** 8

---

### ASMA029E Incorrect register specification - xxxxxxxx

**Explanation:** The value xxxxxxxx is invalid for one of the following reasons:

- xxxxxxxx is not an absolute value within the range 0 through 15.
- an odd register is used where an even register is required
- a register is not specified where one is required.

**System action:** For machine instructions and S-type

## Assembly error diagnostic messages

address constants, the statement or constant assembles as zero. For USING and DROP statements, the incorrect register operand is ignored.

**Programmer response:** Specify a valid register.

**Severity:** 8

---

### ASMA030E Invalid literal usage - xxxxxxxx

**Explanation:** A literal is used in an assembler instruction, another literal, or a field of a machine instruction where it is not permitted.

**System action:** An assembler instruction containing a literal is generally ignored and another message, relative to the operation code of the instruction, appears. A machine instruction assembles as zero.

**Programmer response:** If applicable, replace the literal with the name of a DC statement.

**Severity:** 8

---

### ASMA031E Invalid immediate or mask field

**Explanation:** The value of an immediate or mask operand of a machine instruction requires more bits to represent it than allowed by the instruction, or the value of the immediate operand exceeds 9 on an SRP instruction or 15 on an MC instruction.

Immediate fields used in an arithmetic context are allowed to be signed, those in a logical context are not; for example:

```
AHI r1,-30000    is valid, but
AHI r1,50000     is not
```

```
TMH r1,50000     is valid, but
TMH r1,-30000    is not
```

**System action:** The instruction assembles as zero.

**Programmer response:** Use a valid immediate operand, or specify the immediate information in a DC statement or a literal and change the statement to a non-immediate type.

**Severity:** 8

---

### ASMA032E Relocatable value or unresolved symbol found when absolute value required

**Explanation:** One of the following has occurred:

- A relocatable or complex relocatable expression is used where an absolute expression is required.
- A DSECT-based expression is used as an operand for an address constant where an expression that resolves into a storage address is required.
- The expression is not resolvable due to a dependency on another symbol that is not yet resolved.

**System action:** A machine instruction assembles as zero. In a DC, DS, or DXD statement, the operand in error and the following operands are ignored.

**Programmer response:** Supply an absolute expression or term, or for an address constant supply a valid storage address expression, or remove dependency on unresolved symbol.

**Severity:** 8

---

### ASMA033I Storage alignment for xxxxxxxx unfavorable

**Explanation:** An address referenced by this statement might not be aligned to the optimal boundary for this instruction; for example, the data referenced by a load instruction (L) might be on a halfword boundary.

**System action:** The instruction assembles as written.

**Programmer response:** Correct the operand if it is in error. If you are using an instruction that does not require alignment, or you want to suppress alignment checking for some other reason, you can specify the NOALIGN assembler option or ACONTROL FLAG(NOALIGN). If a particular statement is correct, you can suppress this message by writing the statement with an absolute displacement and an explicit base register, as in this example:

```
L    1,SYM-BASE(,2)
```

**Severity:** 0

---

### ASMA034E Operand *operand* beyond active USING range by xxxx bytes

**Explanation:** The address of this statement does not fall within the range of an active USING statement.

**System action:** The instruction assembles as zero.

**Programmer response:** Increase the range of the active USING.

**Severity:** 8

---

### ASMA035S Invalid delimiter - xxxxxxxx

**Explanation:**

1. A required delimiter in a DC, DS, or DXD statement is missing or appears where none should be; the error might be any of these:
  - A quotation mark with an address constant.
  - A left parenthesis with a non-address constant.
  - A constant field not started with a quotation mark, left parenthesis, space, or comma.
  - An empty constant field in a DC.
  - A missing comma or right parenthesis following an address constant.
  - A missing subfield right parenthesis in an S-type address constant.
  - A missing right parenthesis in a constant modifier expression.
2. A parameter in a macro prototype statement was not followed by a valid delimiter: comma, equal sign, or space.

3. The DBCS option is on, and SO follows a variable symbol without an intervening period.

**System action:** The operand or parameter in error and the following operands or parameters are ignored.

**Programmer response:** Supply a valid delimiter.

**Severity:** 12

---

### ASMA036W Reentrant check failed

**Explanation:** A machine instruction that might store data into a control section or common area when run has been detected. This message is generated only when reentrant checking is requested by the assembler option RENT or within an RSECT.

**System action:** The statement assembles as written.

**Programmer response:** If you want reentrant code, correct the instruction. Otherwise, for a control section that has not been defined by an RSECT instruction, you can suppress reentrancy checking by specifying NORENT as an assembler option. You cannot suppress reentrancy checking for a control section defined by an RSECT instruction.

**Severity:** 4

---

### ASMA037E Illegal self-defining value - xxxxxxxx

**Explanation:** A decimal, binary (B), hexadecimal (X), or character (C) self-defining term contains characters that are not permitted or is in illegal format.

**System action:** In the source program, the operand in error and the following operands are ignored. In a macro definition, the whole statement is ignored.

**Programmer response:** Supply a valid self-defining term.

**Severity:** 8

---

### ASMA038S Operand value falls outside of current section/LOCTR

**Explanation:** An ORG statement specifies a location outside the control section or the LOCTR in which the ORG is used. ORG cannot force a change to another section or LOCTR.

**System action:** The statement is ignored.

**Programmer response:** Change the ORG statement if it is wrong. Otherwise, insert a CSECT, DSECT, COM, or LOCTR statement to set the location counter to the correct section before the ORG statement is processed.

**Severity:** 12

---

### ASMA039S Location counter error

**Explanation:** The maximum location counter value has been exceeded. When the OBJECT or DECK assembler option is specified the maximum location counter value is 'X'FFFFFF'.

When the GOFF assembler option is specified the maximum location counter value is 'X'7FFFFFFF'.

**System action:** The assembly continues, however, the resulting code will probably not run correctly.

**Programmer response:** The probable cause is a high ORG statement value or a high START statement value. Correct the value or split up the control section.

**Severity:** 12

---

### ASMA040S Missing operand

**Explanation:** The statement requires an operand, and none is present.

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored.

**Programmer response:** Supply the missing operand.

**Severity:** 12

---

### ASMA041E Term expected; text is unclassifiable - xxxxxxxx

**Explanation:** One of these errors has occurred:

- A term was expected, but the character encountered is not one that starts a term (letter, number, =, +, -, \*).
- A letter and a quotation mark did not introduce a valid term; the letter is not L, C, G (DBCS option), X, or B.

**System action:** Another message accompanies an assembler statement. A machine instruction assembles as zero.

**Programmer response:** Check for missing punctuation, a wrong letter on a self-defining term, a bad attribute request, a leading comma, or a dangling comma. Note that the length attribute is the only one accepted here. If a defined, scale, type, or integer attribute is needed, use a SETA statement and substitute the variable symbol where the attribute is needed.

**Severity:** 8

---

### ASMA042W Length attribute of symbol is unavailable; default=1 - xxxxxxxx

**Explanation:** This statement has a length attribute reference to a symbol, and the length attribute of the symbol is unavailable for one of the following reasons:

- The symbol has not been previously defined.
- The type attribute of a symbol is U.



## Assembly error diagnostic messages

A symbol defined by an EQU instruction has a type attribute of U, however, a reference to its length does not produce this message.

- The length cannot be determined due to lookahead processing. If a statement that defines a symbol, and references a length attribute, causes lookahead processing, the symbol might not be assigned a length attribute until after lookahead processing is complete. References to the same length attribute in subsequent conditional assembly statements, before lookahead processing completes, might cause this message to be produced.

**System action:** The L' attribute defaults to 1.

**Programmer response:** Ensure the symbol is defined. If you suspect the error might be caused because of lookahead processing, restructure your code so that the symbol is defined before it is referenced.

| **Severity:** 4

---

### ASMA043E Previously defined symbol - xxxxxxxx

**Explanation:** The symbol in a name field or in the operand field of an EXTRN or WXTRN statement was defined (used as a name or an EXTRN/WXTRN operand) in a previous statement.

**System action:** The name or EXTRN/WXTRN operand of this statement is ignored. The following operands of an EXTRN or WXTRN are processed. The first occurrence of the symbol defines it.

**Programmer response:** Correct a possible spelling error, or change the symbol.

**Severity:** 8

---

### ASMA044E Undefined symbol - xxxxxxxx

**Explanation:** A symbol in the operand field has not been defined, that is, used in the name field of another statement, the operand field of an EXTRN or WXTRN, or, in the case of a literal, the operand of a previously processed machine instruction statement.

**System action:** A machine instruction or an address constant assembles as zero. In a DC, DS, or DXD statement or in a duplication-factor or length- modifier expression, the operand in error and the following operands are ignored. In an EQU statement, zero is assigned as the value of the undefined symbol. Any other instruction is not processed.

**Programmer response:** Define the symbol, or remove the references to it.

**Severity:** 8

---

### ASMA045W Register or label not previously used - xxxxxxxx

**Explanation:** A register or label specified in a DROP statement has not been previously specified in a USING statement.

**System action:** Registers or labels not active at the time are ignored.

**Programmer response:** Remove the unreferenced registers or label from the DROP statement. You can drop all active base registers and labels at once by specifying DROP with a blank operand.

**Severity:** 4

---

### ASMA046E Bit 7 of CCW flag byte must be zero

**Explanation:** Bit 7 of the flag byte of a channel command word specified by a CCW, CCW0, or CCW1 statement is not zero.

**System action:** The CCW, CCW0, or CCW1 assembles as zero.

**Programmer response:** Set bit 7 of the flag byte to zero to suppress this message during the next assembly.

**Severity:** 8

---

### ASMA047E Severity code too large

**Explanation:** The severity code (first operand) of an MNOTE statement is not \* or an unsigned decimal number from 0 to 255.

**System action:** The statement is printed in standard format instead of MNOTE format. The MNOTE is given the severity code of this message.

**Programmer response:** Choose a severity code of \* or a number less than or equal to 255, or check for a generated severity code.

**Severity:** 8

---

### ASMA048E ENTRY error - xxxxxxxx

**Explanation:** One of the following errors was detected in the operand of an ENTRY statement:

- Duplicate symbol (previous ENTRY)
- Symbol defined in a DSECT or COM section
- Symbol defined by a DXD statement
- Undefined symbol
- Symbol defined by an absolute or complex relocatable EQU statement
- Symbol lies outside the bounds of the section in which it is defined

**System action:** The external symbol dictionary output is suppressed for the symbol.

**Programmer response:** Define the ENTRY operand correctly.

Severity: 8

---

## ASMA049W Illegal range on ISEQ

**Explanation:** If this message is accompanied by another, this one is advisory. If it appears by itself, it indicates one of the following errors:

- An operand value is less than 1 or greater than 80, or the second operand (rightmost column to be checked) is less than the first operand (extreme left column to be checked).
- More or fewer than two operands are present, or an operand is null (empty).
- An operand expression contains an undefined symbol.
- An operand expression is not absolute.
- The statement is too complex. For example, it might have forward references or cause an arithmetic overflow during evaluation.
- The statement is circularly defined.

**System action:** Sequence checking stops.

**Programmer response:** Supply valid ISEQ operands. Also, be sure that the records following this statement are in order; they have not been sequence checked.

Severity: 4

---

## ASMA050E Illegal name field; name discarded - xxxxxxxx

**Explanation:** One of these errors has occurred:

- The name field of a macro prototype statement contains an incorrect symbolic parameter (variable symbol)
- The name field of a COPY statement in a macro definition contains an entry other than space or a valid sequence symbol

**System action:** The incorrect name field is ignored.

**Programmer response:** Correct the incorrect name field.

Severity: 8

---

## ASMA051E Illegal statement outside a macro definition

**Explanation:** A MEND, MEXIT, ASPACE, AEJECT or AREAD statement appears outside a macro definition.

**System action:** The statement is ignored.

**Programmer response:** Remove the statement or, if a macro definition is intended, insert a MACRO statement.

Severity: 8

---

## ASMA052S Record out of sequence - xxxxxxxx

**Explanation:** Input sequence checking, under control of the ISEQ assembler instruction, has determined that this statement is out of sequence. The sequence number of the statement is appended to the message.

**System action:** The statement assembles normally. However, the sequence number of the next statement is checked relative to this statement.

**Programmer response:** Put the statements in correct sequence. If you want a break in sequence, put in a new ISEQ statement and sequence number. ISEQ always resets the sequence number; the record following the ISEQ is not sequence checked.

Severity: 12

---

## ASMA053W Blank sequence field - xxxxxxxx

**Explanation:** Input sequence checking, controlled by the ISEQ assembler statement, has detected a statement with a blank sequence field. The sequence number of the last numbered statement is appended to the message.

**System action:** The statement assembles normally. The sequence number of the next statement is checked relative to the last statement having a non-blank sequence field.

**Programmer response:** Put the correct sequence number in the statement or discontinue sequence checking over the blank statements by means of an ISEQ statement with a blank operand.

Severity: 4

---

## ASMA054E Illegal continuation record

**Explanation:** A statement has more than 10 records or end-of-input has been encountered when a continuation record was expected.

**System action:** The records already read are processed as is. If the statement had more than 10 records, the next record is treated as the beginning of a new statement.

**Programmer response:** In the first case, break the statement into two or more statements. In the second case, ensure that a continued statement does not span the end of a library member. Check for lost records or an extraneous continuation character.

Severity: 8

---

## ASMA055S Recursive COPY

**Explanation:** A nested COPY statement (COPY within another COPY) attempted to copy a library member already being copied by a higher level COPY within the same nest.

## Assembly error diagnostic messages

**System action:** This COPY statement is ignored.

**Programmer response:** Correct the operand of this COPY if it is wrong, or rearrange the nest so that the same library member is not copied by COPY statements at two different levels.

**Severity:** 12

---

### ASMA056W Absolute value found when relocatable value expected - xxxxxxxx

**Explanation:** An absolute expression has been used as the immediate field in a branch-relative instruction. The immediate field in a branch-relative instruction is used as signed number of halfwords relative to the current location counter. The use of an absolute expression for this value may cause unpredictable results.

**System action:** The instruction assembles as written.

**Programmer response:** Supply a relocatable expression.

**Severity:** 4

---

### ASMA057E Undefined operation code - xxxxxxxx

**Explanation:** One of the following errors has occurred:

- The operation code of this statement is not a valid machine or assembler instruction or macro name.
- In an OPSYN statement, this operand symbol is undefined or illegal or, if no operand is present, the name field symbol is undefined.
- On z/VSE the High Level Assembler only reads library macros that have a member type of A, or if the // OPTION SUBLIB=DF statement is used, a member type of D. Edited (E-Deck) macros, that have a member type of E or F can only be read by a LIBRARY exit.

**System action:** The statement is ignored. Note that OPSYN does not search the macro library for an undefined operand.

**Programmer response:** Correct the statement. In the case of an undefined macro instruction, the wrong data set might have been specified for the macro library. In the case of OPSYN, a previous OPSYN or macro definition might have failed to define the operation code.

If the operation code shown is a z/VSE edited macro (E-Deck), High Level Assembler can only find and read it with a LIBRARY exit. You might want to use the z/VSE supplied LIBRARY exit described in VSE/ESA Guide to System Functions.

**Severity:** 8

---

### ASMA058E Invalid relative address - xxxxxxxx

**Explanation:** One of the following has occurred:

- The relative address is an odd value, and therefore cannot be represented as a number of halfwords.
- The NOGOFF option has been specified and the relative address is not in the same control section as the instruction.
- The relative address has the same relocatability attribute as the instruction, but is outside the control section.

**System action:** The instruction assembles as zero.

**Programmer response:** Supply a valid relative address that is on a halfword boundary and within the same control section. To allow a relative address that is outside the current control section, specify the GOFF option.

**Severity:** 8

---

### ASMA059C Illegal ICTL - xxxxxxxx

**Explanation:** An ICTL statement has one of the following errors:

- The operation code was created by variable symbol substitution
- It is not the first statement in the assembly
- The value of one or more operands is incorrect
- An operand is missing
- A character is detected in the operand field that is not permitted

**System action:** The ICTL statement is ignored. Assembly continues with standard ICTL values.

**Programmer response:** Correct or remove the ICTL. The begin column must be 1-40; the end column must be 41-80 and at least five greater than the begin column; and the continue column must be 2-40.

**Severity:** 16

---

### ASMA060S COPY code not found - xxxxxxxx

**Explanation:** (1) If this message is on a COPY statement and no text is printed with it, one of the following occurred:

- The library member was not found.
- The lookahead phase previously processed the COPY statement and did not find the library member, the copy was recursive, or the operand contains a variable symbol. Variable symbols can be used if the COPY statement is in open code.

(2) If this message is not on a COPY statement, but has a library member name printed with it, the lookahead phase of the assembler could not find the library member because the name is undefined or contains a variable symbol.

**System action:** The COPY statement is ignored; the library member is not copied.



**Programmer response:** Check that the correct macro library was assigned, or check for a possible misspelled library member name.

If COPY member is not defined in any macro library, and is not processed because of an AGO or AIF assembler instruction, add a dummy COPY member with the name to the macro library.

**Severity:** 12

---

### ASMA061E Symbol not name of DSECT, DXD or external label

**Explanation:** The operand of a Q-type address constant is not a symbol or the name of a DSECT or DXD statement, or an external label.

**System action:** The constant assembles as zero.

**Programmer response:** Supply a valid operand.

**Severity:** 8

---

### ASMA062E Illegal operand format - xxxxxxxx

**Explanation:** One of the following errors has occurred:

- ADATA—more than five operands are specified, or the value of one of the expressions specified in one of the first four operands is outside the range  $-2^{31}$  to  $+2^{31}-1$ , or the fifth operand is not a valid character expression
- ACONTROL—one or more of the operands supplied is invalid
- AINSERT—the first operand is not a valid string, or the second operand is not BACK or FRONT
- AMODE—the operand does not specify 24, 31, or ANY
- AREAD—the operand specifies an incorrect AREAD operand.
- DROP or USING—more than 16 registers are specified in the operand field
- EXITCTL—more than five operands are specified, or the first operand is not a valid exit type, or the value of one of the expressions specified in the second and subsequent operands is outside the range  $-2^{31}$  to  $+2^{31}-1$
- MNOTE—the syntax of the severity code (first operand) is not correct, or the sum of the length of the operands including quotes and commas exceeds 1024 bytes
- PRINT—an operand specifies an incorrect print option
- PUSH or POP—an operand does not specify a PRINT or USING statement
- RMODE—the operand does not specify 24 or ANY
- TITLE—more than 100 bytes were specified

**System action:** The first 16 registers in a DROP or USING statement are processed. The operand in error and the following operands of a PUSH, POP, or PRINT statement are ignored. The AMODE or RMODE instruction is ignored, and the name field (if any) does not appear in the cross-reference listing. The first 100

bytes of the operand of the TITLE instruction are used as the title.

**Programmer response:** Supply a valid operand field.

**Severity:** 8

---

### ASMA063E No ending apostrophe - xxxxxxxx

**Explanation:** The quotation mark terminating an operand is missing, or the standard value of a keyword parameter of a macro prototype statement is missing.

**System action:** The operand or standard value in error is ignored. If the error is in a macro definition model statement, the whole statement is ignored.

**Programmer response:** Supply the missing quotation mark.

**Severity:** 8

---

### ASMA064S Floating point characteristic out of range

**Explanation:** A converted floating-point constant is too large or too small for the processor. The allowable range is approximately  $5.4 \times 10^{-79}$  to  $7.2 \times 10^{75}$ .

**System action:** The constant assembles as zero.

**Programmer response:** Check the characteristic (exponent), exponent modifier, scale modifier, and mantissa (fraction) for validity. Remember that a floating-point constant is rounded, not truncated, after conversion.

**Severity:** 12

---

### ASMA065E Unknown type - xxxxxxxx

**Explanation:** An unknown constant type has been used in a DC or DS statement or in a literal, or the assembler option required to support the constant type has not been supplied.

**System action:** The operand in error and the following operands are ignored.

**Programmer response:** Supply a valid constant or the required assembler option. Look for an incorrect type code or incorrect syntax in the duplication factor.

**Severity:** 8

---

### ASMA066W 2-byte relocatable address constant

**Explanation:** This statement contains a relocatable Y-type address constant or a 2-byte relocatable A-type address constant. Addressing errors occur if the address constant is used to refer to a storage address equal to or greater than 64K (65,536).

**System action:** The statement assembles as written.

**Programmer response:** If the address constant is used to refer to a storage address less than 64K (65,536), the 2-byte relocatable address constant is valid. You can use

## Assembly error diagnostic messages

the assembler option RA2 to suppress this message.

**Severity:** 4

---

### ASMA067S Illegal duplication factor - xxxxxxxx

**Explanation:** One of the following errors has occurred:

- A literal has a zero duplication factor
- The duplication factor of a constant is greater than the maximum of  $2^{24}-1$  bytes
- A duplication factor expression of a constant is not correct

**System action:** The operand in error and the following operands of a DC, DS, or DXD statement are ignored. The statement containing the literal assembles as zero.

**Programmer response:** Supply a valid duplication factor. If you want a zero duplication factor, write the literal as a DC statement.

**Severity:** 12

---

### ASMA068S Length error - xxxxxxxx

**Explanation:** One of the following errors has occurred:

- The length modifier of a constant is wrong
- The C, X, B, Z, or P-type constant is too long
- An operand is longer than  $2^{24}-1$  bytes
- A relocatable address constant has an illegal length
- The length field in a machine instruction is not correct or is out of the permissible range
- The length modifier of a Character Unicode constant is not a multiple of 2

**System action:**

- A machine instruction assembles as zero
- A new floating point constant assembles as zero
- An address constant is truncated
- For other DC, DS or DXD statements, the operand in error and the following operands are ignored
- The operand in error, and the operands following, are ignored.

**Programmer response:** Supply a valid length or correct the length modifier.

**Severity:** 12

---

### ASMA069S Length of second operand must be less than length of first

**Explanation:** The length of the second operand must be less than the length of the first operand. If it is not, a specification exception is recognized.

**System action:** The machine instruction assembles as zero.

**Programmer response:** Supply a second operand with a length which is less than that of the first operand.

**Severity:** 12

---

### ASMA070E Scale modifier error - xxxxxxxx

**Explanation:** A scale modifier in a constant is used illegally, is out of range, or is relocatable, or there is an error in a scale modifier expression.

**System action:** If the scale modifier is out of range, it defaults to zero. Otherwise, the operand in error and the following operands are ignored.

**Programmer response:** Supply a valid scale modifier.

**Severity:** 8

---

### ASMA071E Exponent modifier error

**Explanation:** The constant contains multiple internal exponents, the exponent modifier is out of range or relocatable, or the sum of the exponent modifier and the internal exponent is out of range.

**System action:** If the constant contains multiple internal exponents, the operand in error and the following operands are ignored. Otherwise, the exponent modifier defaults to zero.

**Programmer response:** Change the exponent modifier or the internal exponent.

**Severity:** 8

---

### ASMA072E Data item too large

**Explanation:** The value of a Y-type address constant or H-type constant is larger than  $2^{15}-1$  or smaller than  $-2^{15}$ , or the value of a F-type constant is larger than  $2^{31}-1$  or smaller than  $-2^{31}$ .

**System action:** The constant is truncated. The high-order bits are lost.

**Programmer response:** Supply a smaller scale modifier, a longer constant, or a smaller value.

**Severity:** 8

---

### ASMA073E Precision lost

**Explanation:** The modifiers of a floating-point number either truncate the exponent or shift the fraction out of the converted constant.

**System action:** The constant assembles with an exponent but with a fraction of zero.

**Programmer response:** Change the modifier or use a longer constant type.

**Severity:** 8

---

### ASMA074E Illegal syntax in expression - xxxxxxxx

**Explanation:** An expression has two terms or two operations in succession, or incorrect or missing characters or delimiters.

**System action:** In a DC, DS, or DXD statement, the

operand in error and the following operands are ignored. In a macro definition, the whole statement is ignored. A machine instruction assembles as zero.

**Programmer response:** Check the expression for typing errors, or for missing or incorrect terms or characters.

**Severity:** 8

### ASMA075E Arithmetic overflow

**Explanation:** The intermediate or final value of an expression is not within the range  $-2^{31}$  through  $2^{31}-1$ .

**System action:** A machine instruction assembles as zero; an assembler instruction is ignored; a conditional assembly expression uses zero as the result.

**Programmer response:** Change the expression.

**Severity:** 8

### ASMA076E Statement complexity exceeded

**Explanation:** The complexity of this statement caused the assembler's expression evaluation work area to overflow.

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored.

**Programmer response:** Reduce the number of terms, levels of expressions, or references to complex relocatable EQU names.

**Severity:** 8

### ASMA077E Circular definition

**Explanation:** The value of a symbol in an expression is dependent on itself, either directly or indirectly, via one or more EQU statements. In the following example:

```
A EQU B
B EQU C
C EQU A
```

A is circularly defined.

**System action:** The value of the EQU statement defaults to the current value of the location counter. All other EQU statements involved in the circularity are defaulted in terms of this one.

**Programmer response:** Supply a correct definition.

**Severity:** 8

### ASMA078E Operand *op* expression complexly relocatable - *expr*

**Explanation:** The expression specified is complexly relocatable, but an absolute or simply relocatable expression is required.

**System action:** The instruction assembles as zero.

**Programmer response:** Correct the expression.

**Severity:** 8

### ASMA079E Illegal PUSH-POP

**Explanation:** More POP assembler instructions than PUSH instructions have been encountered.

**System action:** This POP instruction is ignored.

**Programmer response:** Eliminate a POP statement, or add another PUSH statement.

**Severity:** 8

### ASMA080E Statement is unresolvable

**Explanation:** A statement cannot be resolved, because it contains a complex relocatable expression or because the location counter has been circularly defined.

**System action:** The statement is ignored.

**Programmer response:** Untangle the forward references or check the complex relocatable EQU statements.

**Severity:** 8

### ASMA081E Created SET symbol exceeds 63 characters - xxxxxxxx

**Explanation:** A SET symbol created by variable symbol substitution is longer than 63 characters (including the ampersand as the first character).

**System action:** If the symbol is in the operand field of a SET, AIF, or AGO statement, its value is set to zero or null, and the type attribute is set to undefined (U). If the symbol is in the operand field of a GBL, or LCL statement or the name field of a SET statement, processing of the macro stops.

**Programmer response:** Shorten the symbol.

**Severity:** 8

### ASMA082E Created SET symbol is null - xxxxxxxx

**Explanation:** A SET symbol created by variable symbol substitution is null (empty string).

**System action:** If the symbol is in the operand field of a SET, AIF, or AGO statement, its value is set to zero or null, and the type attribute is set to undefined (U). If the symbol is in the operand field of a GBL, or LCL statement or the name field of a SET statement, processing of the macro stops.

**Programmer response:** Supply a valid symbol.

**Severity:** 8

## Assembly error diagnostic messages

---

### ASMA083E Created SET symbol is not a valid symbol - xxxxxxxx

**Explanation:** A SET symbol created by variable symbol substitution or concatenation does not consist of an ampersand followed by up to 62 alphanumeric characters, the first of which is alphabetic.

**System action:** If the symbol is in the operand field of a SET, AIF, or AGO statement, its value is set to zero or null, and the type attribute is set to undefined (U). If the symbol is in the operand field of a GBL or LCL statement or the name field of a SET statement, processing of the macro stops.

**Programmer response:** Supply a valid symbol.

**Severity:** 8

---

### ASMA084S Generated name field exceeds 63 characters; discarded - xxxxxxxx

**Explanation:** The name field on a generated statement is longer than 63 characters.

**System action:** The name field is not generated. The rest of the statement assembles normally.

**Programmer response:** Shorten the generated name to 63 characters or fewer.

**Severity:** 12

---

### ASMA085I Generated operand field is null - xxxxxxxx

**Explanation:** The operand field of a generated machine instruction is null (empty). This message is not issued for generated macro instructions.

**System action:** The statement assembles as though no operand were specified.

**Programmer response:** Provide a non-empty operand field. If you want the statement assembled with no operand, substitute a comma rather than leave the operand blank.

**Severity:** 0

---

### ASMA086S Missing MEND generated - xxxxxxxx

**Explanation:** A macro definition, appearing in the source program or being read from a library by a macro call or a COPY statement, ends before a MEND statement is encountered to end it.

**System action:** A MEND statement is generated. The portion of the macro definition read in is processed.

**Programmer response:** Insert the MEND statement if it was omitted. Otherwise, check if all the macro definition is on the library.

**Severity:** 12

---

### ASMA087S Generated operation code is null - xxxxxxxx

**Explanation:** The operation code of a generated statement is null (blank).

**System action:** The generated statement is printed but not assembled.

**Programmer response:** Provide a valid operation code.

**Severity:** 12

---

### ASMA088E Unbalanced parentheses in macro call operand - xxxxxxxx

**Explanation:** Excess left or too few right parentheses occur in an operand (parameter) of a macro call statement.

**System action:** The parameter corresponding to the operand in error is given a null (empty) value.

**Programmer response:** Balance the parentheses.

**Severity:** 8

---

### ASMA089E Arithmetic expression contains illegal delimiter or ends prematurely - xxxxxxxx

**Explanation:** An arithmetic expression contains an incorrect character or an arithmetic subscript ends without enough right parentheses.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid expression.

**Severity:** 8

---

### ASMA090E Excess right parenthesis in macro call operand - xxxxxxxx

**Explanation:** A right parenthesis without a corresponding left parenthesis was detected in an operand of a macro instruction.

**System action:** The excess right parenthesis is ignored. The macro expansion might be incorrect.

**Programmer response:** Insert the correct parenthesis.

**Severity:** 8

---

### ASMA091E Character string exceeds maximum length; truncated to maximum - xxxxxxxx

**Explanation:** The value of the operand of a SETC or SETCF statement or the character relational operand of an AIF statement is longer than 1024 characters. This might occur before substrings are evaluated.

**System action:** The first 1024 characters are used.

**Programmer response:** Shorten the SETC or SETCF expression value or the operand value.

Severity: 8

---

**ASMA092E Substring expression 1 points past string end; default=null - xxxxxxxx**

**Explanation:** The first arithmetic expression of a SETC substring points beyond the end of the expression character string.

**System action:** The substring is given a null value.

**Programmer response:** Supply a valid expression.

Severity: 8

---

**ASMA093E Substring expression 1 less than 1; default=null - xxxxxxxx**

**Explanation:** The first arithmetic expression of a SETC substring is less than one; that is, it points before the expression character string.

**System action:** The substring expression defaults to null.

**Programmer response:** Supply a valid expression.

Severity: 8

---

**ASMA094I Substring goes past string end; default=remainder**

**Explanation:** The second expression of a substring notation specifies a length that extends beyond the end of the string.

**System action:** The result of the substring operation is a string that ends with the last character in the character string.

**Programmer response:** Make sure the arithmetic expression used to specify the length does not specify characters beyond the end of the string. Either change the first or the second expression in the substring notation. You can use the assembler option FLAG(NOSUBSTR) to suppress this message.

Severity: 0

---

**ASMA095W Substring expression 2 less than 0; default=null - xxxxxxxx**

**Explanation:** The second arithmetic expression of a SETC substring is less than or equal to zero.

**System action:** No characters (a null string) from the substring character expression are used.

**Programmer response:** Supply a valid expression.

Severity: 4

---

**ASMA096E Unsubscripted SYSLIST; default=SYSLIST(1) - xxxxxxxx**

**Explanation:** The system variable symbol, &SYSLIST, is not subscripted. &SYSLIST(n) refers to the *n*th positional parameter in a macro instruction. N'&SYSLIST does not have to be subscripted.

**System action:** The subscript defaults to one so that it refers to the first positional parameter.

**Programmer response:** Supply the correct subscript.

Severity: 8

---

**ASMA097E Invalid attribute reference to SETA or SETB symbol; default=U or 0 - xxxxxxxx**

**Explanation:** A length (L'), scaling (S'), integer (I'), or defined (D') attribute refers to a SETA or SETB symbol.

**System action:** The attributes are set to default values: L'=0, S'=0, I'=0, and D'=0.

**Programmer response:** Change or remove the attribute reference.

Severity: 8

---

**ASMA098E Attribute reference to invalid symbol; default=U or 0 - xxxxxxxx**

**Explanation:** An attribute attempted to reference a symbol that is not correct or has a null value. (A valid symbol is 1 to 63 alphanumeric characters, the first of which is alphabetic.)

**System action:** For a type (T') attribute, defaults to U. For all other attributes, defaults to 0.

**Programmer response:** Supply a valid symbol.

Severity: 8

---

**ASMA099W Wrong type of constant for S or I attribute reference; default=0 - xxxxxxxx**

**Explanation:** An integer (I') or scaling (S') attribute references a symbol whose type is other than floating-point (E,D,L), decimal (P,Z), or fixed-point (H,F).

**System action:** The integer or scaling attribute defaults to zero.

**Programmer response:** Remove the integer or scaling attribute reference or change the constant type.

Severity: 4

---

**ASMA100E Subscript less than 1; default to subscript=1 - xxxxxxxx**

**Explanation:** The subscript of a subscripted SET symbol in the name field of a SET statement, the operand field of a GBL or LCL statement, or an



## Assembly error diagnostic messages

&SYSLIST statement is less than 1.

**System action:** The subscript defaults to 1.

**Programmer response:** Supply the correct subscript.

**Severity:** 8

---

**ASMA101E Subscript less than 1; default to value=0 or null - xxxxxxxx**

**Explanation:** The subscript of a SET symbol in the operand field is less than 1.

**System action:** The value is set to zero or null.

**Programmer response:** Supply a valid subscript.

**Severity:** 8

---

**ASMA102E Arithmetic term is not self-defining term; default=0 - xxxxxxxx**

**Explanation:** A SETC term or expression used as an arithmetic term is not a valid self-defining term.

**System action:** The value of the SETC term or expression is set to zero.

**Programmer response:** Make the SETC a self-defining term, such as C'A', X'1EC', B'1101', or 27. The C, X, or B and the quotation marks must be part of the SETC value.

**Severity:** 8

---

**ASMA103E Multiplication overflow; default product=1 - xxxxxxxx**

**Explanation:** A multiplication overflow occurred in a macro definition statement.

**System action:** The value of the expression up to the point of overflow is set to one; evaluation continues.

**Programmer response:** Change the expression so that overflow does not occur; break it into two or more operations, or regroup the terms by parentheses.

**Severity:** 8

---

**ASMA104W Statement processing incomplete**

**Explanation:** This indicates that a previously-flagged error has terminated processing for this statement.

**System action:** The assembly continues.

**Programmer response:** Correct previous errors.

**Severity:** 4

---

**ASMA105U Arithmetic expression too complex**

**Explanation:** An arithmetic expression in a macro definition statement caused an internal workarea

overflow because it is too complex; that is, it has too many terms, levels, or both.

**System action:** The assembly stops.

**Programmer response:** Simplify the expression or break it into two or more expressions.

**Severity:** 20

---

**ASMA106E Wrong target symbol type; value left unchanged - xxxxxxxx**

**Explanation:** The SET symbol in the name field has already been declared, and is a different type to the type of SETx instruction. For example, you might have previously declared a SET symbol as arithmetic (SETA), and you are attempting to use the SET symbol as the target of a SETC instruction.

**System action:** The statement is ignored.

**Programmer response:** Make the declaration agree with the SET statement type. If you want to store across SET symbol types, first store into a SET symbol of matching type, and then use another SETx instruction to store the value, represented by the matching SET symbol, into the non- matching SET symbol.

**Severity:** 8

---

**ASMA107E Inconsistent dimension on target symbol; subscript ignored, or 1 used - xxxxxxxx**

**Explanation:** The SET symbol in the name field is dimensioned (subscripted), but was not declared in a GBL or LCL statement as dimensioned, or vice versa.

**System action:** The subscript is ignored or a subscript of 1 is used, in accordance with the declaration.

**Programmer response:** Make the declaration and the usage compatible. Note that you can declare a local SET symbol as dimensioned by using it, subscripted, in the name field of a SET statement.

**Severity:** 8

---

**ASMA108E Inconsistent dimension on SET symbol reference; default = 0, null, or type=U - xxxxxxxx**

**Explanation:** A SET symbol in the operand field is dimensioned (subscripted), but was not declared in a GBL or LCL statement as dimensioned, or vice versa.

**System action:** A value of zero or null is used for the subscript. If the type attribute of the SET symbol is requested, it is set to U.

**Programmer response:** Make the declaration and the usage compatible. You can declare a SET symbol as dimensioned by using it, subscripted, in the name field of a SET statement.

Severity: 8

---

**ASMA109E Multiple SET operands for undimensioned SET symbol; gets last operand - xxxxxxxx**

**Explanation:** Multiple operands were assigned to an undimensioned (unsubscripted) SET symbol.

**System action:** The SET symbol is given the value of the last operand.

**Programmer response:** Declare the SET symbol as dimensioned, or assign only one operand to it.

Severity: 8

---

**ASMA110S Library macro first statement not 'MACRO' or comment**

**Explanation:** A statement other than a comment statement preceded a MACRO statement in a macro definition read from a library.

**System action:** The macro definition is not read from the library. A corresponding macro call cannot be processed.

**Programmer response:** Ensure that the library macro definition begins with a MACRO statement preceded (optionally) by comment statements only.

Severity: 12

---

**ASMA111S Invalid AIF or SETB operand field - xxxxxxxx**

**Explanation:** The operand of an AIF or SETB statement either does not begin with a left parenthesis or is missing altogether.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid operand.

Severity: 12

---

**ASMA112S Invalid sequence symbol - xxxxxxxx**

**Explanation:** One of the following errors has occurred:

- A sequence symbol does not begin with a period followed by one to 62 alphanumeric characters, the first being alphabetic.
- A sequence symbol in the name field was created by substitution.
- Operand of AGO is blank or sequence symbol in AIF is blank.

**System action:** The sequence symbol in the name field is ignored. A sequence symbol in the operand field of an AIF or AGO statement causes the whole statement to be ignored.

**Programmer response:** Supply a valid sequence symbol.

Severity: 12

---

**ASMA113S Continue column blank**

**Explanation:** A SET symbol declaration in a GBL or LCL statement began with an ampersand in the end column (normally column 71) of the previous record, but the continue column (normally column 16) of this record is blank.

**System action:** This record and any following records of the statement are ignored. Any SET symbols that completely appear on the previous record(s), are processed normally.

**Programmer response:** Begin this record in the continuation indicator field.

Severity: 12

---

**ASMA114S Invalid COPY operand - xxxxxxxx**

**Explanation:** The operand of a COPY statement is not a symbol of 1 to 8 alphanumeric characters, the first being alphabetic.

**System action:** The COPY statement is ignored.

**Programmer response:** Supply a valid operand. In open code the operand can be specified as a previously defined SET symbol.

Severity: 12

---

**ASMA115S COPY operand too long - xxxxxxxx**

**Explanation:** The symbol in the operand field of a COPY statement is more than 8 characters long.

**System action:** The COPY statement is ignored.

**Programmer response:** Supply a valid operand.

Severity: 12

---

**ASMA116E Illegal SET symbol - xxxxxxxx**

**Explanation:** A SET symbol in the operand field of a GBL or LCL statement or in the name field of a SET statement does not consist of an ampersand followed by one to 62 alphanumeric characters, the first being alphabetic.

**System action:** For a GBL or LCL statement, the incorrect SET symbol and all following SET symbols in a GBL or LCL statement are ignored. For a SET statement, the whole SET statement is ignored.

**Programmer response:** Supply a SET symbol.

Severity: 8

## Assembly error diagnostic messages

---

### ASMA117E Illegal subscript - xxxxxxxx

**Explanation:** The subscript following a SET symbol contained unbalanced parentheses or an incorrect arithmetic expression.

**System action:** This statement is ignored.

**Programmer response:** Supply an equal number of left and right parentheses or a valid arithmetic expression.

**Severity:** 8

---

### ASMA118S Source macro ended by 'MEND' in COPY code

**Explanation:** A library member, being copied by a COPY statement within a macro definition, contained a MEND statement.

**System action:** The MEND statement is honored and the macro definition stops. No more COPY code is read. The statements brought in before the end of the COPY code are processed.

**Programmer response:** Make sure that each library member to be used as COPY code contains balanced MACRO and MEND statements.

**Severity:** 12

---

### ASMA119S Too few MEND statements in COPY code

**Explanation:** A macro definition is started in a library member brought in by a COPY statement and the COPY code ends before a MEND statement is encountered.

**System action:** A MEND statement is generated to end the macro definition. The statements brought in before the end of the COPY code are processed.

**Programmer response:** Check to see if part of the macro definition was lost. Also, ensure that each macro definition to be used as COPY code contains balanced MACRO and MEND statements.

**Severity:** 12

---

### ASMA120S EOD where continuation record expected

**Explanation:** An end-of-data occurred when a continuation record was expected.

**System action:** The portion of the statement read in is assembled. The assembly stops if the end-of-data is on the PRIMARY INPUT. If a library member is being copied, the assembly continues with the statement after the COPY statement.

**Programmer response:** Check to determine whether any statements were omitted from the source program or from the COPY code.

**Severity:** 12

---

### ASMA121S Insufficient storage for editor work area

**Explanation:** The macro editor module of the assembler cannot get enough main storage for its work areas.

**System action:** The assembly stops.

**Programmer response:** Split the assembly into two or more parts or give the macro editor more working storage.

on z/OS or CMS, this can be done by increasing the region size for the assembler, decreasing blocking factor or block size on the assembler data sets, or a combination of both.

On z/VSE, this can be done by decreasing the value you specify on the SIZE parameter of the JCL EXEC statement, or by running the assembly in a larger partition.

**Severity:** 12

---

### ASMA122S Illegal operation code format

**Explanation:** The operation code is not followed by a space or is missing altogether, or the first record of a continued source statement is missing.

**System action:** The statement is ignored.

**Programmer response:** Ensure that the statement has a valid operation code and that all records of the statement are present.

**Severity:** 12

---

### ASMA123S Variable symbol too long - xxxxxxxx

**Explanation:** A SET symbol, symbolic parameter, or sequence symbol contains more than 62 characters following the ampersand or period.

**System action:** This statement is ignored.

**Programmer response:** Shorten the SET symbol or sequence symbol.

**Severity:** 12

---

### ASMA124S Illegal use of parameter

**Explanation:** A symbolic parameter was used in the operand field of a GBL or LCL statement or in the name field of a SET statement. In other words, a variable symbol has been used both as a symbolic parameter and as a SET symbol.

**System action:** The statement is ignored.

**Programmer response:** Change the variable symbol to one that is not a symbolic parameter.

**Severity:** 12



---

### ASMA125S    **Illegal macro name - macro uncallable - xxxxxxxx**

**Explanation:** The operation code of a macro prototype statement is not a valid symbol; that is, one to 63 alphanumeric characters, the first alphabetic.

**System action:** The macro definition is edited. However, since the macro name is not correct, the macro cannot be called.

**Programmer response:** Supply a valid macro name.

**Severity:** 12

---

### ASMA126S    **Library macro name incorrect - xxxxxxxx**

**Explanation:** The operation code of the prototype statement of a library macro definition is not the same as the operation code of the macro instruction (call). Library macro definitions are located by their member names. However, the assembler compares the macro instruction with the macro prototype.

**System action:** The macro definition is edited using the operation code of the prototype statement as the macro name. Thus, the definition cannot be called by this macro instruction.

**Programmer response:** Ensure that the member name of the macro definition is the same as the operation code of the prototype statement. This usually requires listing the macro definition from the library, use of the LIBMAC option to cause the macro definition to be listed, or a COPY of the member name.

**Severity:** 12

---

### ASMA127S    **Illegal use of ampersand**

**Explanation:** One of the following errors has occurred:

- An ampersand was found where all substitution should have already been done
- The standard value of a keyword parameter in a macro prototype statement contained a single ampersand or a string with an odd number of ampersands
- An unpaired ampersand occurred in a character (C) constant

**System action:** In a macro prototype statement, all information following the error is ignored. In other statements, the action depends on which field the error occurred in. If the error occurred in the name field, the statement is processed without a name. If the error occurred in the operation code field, the statement is ignored. If the error occurred in the operand field, another message is issued to specify the default. However, if the error occurred in a C-type constant, the operand in error and the following operands are ignored.

**Programmer response:** Ensure that ampersands used in keyword standard values or in C-type constant values occur in pairs. Also, avoid substituting an

ampersand into a statement unless there is a double ampersand.

**Severity:** 12

---

### ASMA128S    **Excess right parenthesis - xxxxxxxx**

**Explanation:** An unpaired right parenthesis has been found.

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored and an additional message relative to the statement type appears. However, if the error is in the standard value of a keyword on a macro prototype statement, only the operands in error and the following operands are ignored.

**Programmer response:** Make sure that all parentheses are paired.

**Severity:** 12

---

### ASMA129S    **Insufficient right parentheses - xxxxxxxx**

**Explanation:** An unpaired left parenthesis has been found. Parentheses must balance at each comma in a multiple operand statement.

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored and an additional message relative to the statement type appears. However, if the error is in the standard value of a keyword on a macro prototype statement, only the operands in error and the following operands are ignored.

**Programmer response:** Make sure that all parentheses are paired.

**Severity:** 12

---

### ASMA130S    **Illegal attribute reference - xxxxxxxx**

**Explanation:** One of the following errors has occurred:

- The symbol following a I, L, S, or T attribute reference is not a valid variable symbol or ordinary symbol or literal that has been previously used in a machine instruction
- The symbol following a K or N attribute reference is not a valid variable symbol
- The symbol following a D or O attribute reference is not a valid variable symbol or ordinary symbol
- The quotation mark is missing from a T attribute reference

**System action:** The statement is ignored.

**Programmer response:** Supply a valid attribute reference.

**Severity:** 12

## Assembly error diagnostic messages

---

### ASMA131S Parenthesis nesting depth exceeds 255 - xxxxxxxx

**Explanation:** There are more than 255 levels of parentheses in a SETA expression.

**System action:** The statement is ignored.

**Programmer response:** Rewrite the SETA statement using several statements to regroup the subexpressions in the expression.

**Severity:** 12

---

### ASMA132S Invalid logical expression - xxxxxxxx

**Explanation:** A logical expression in the operand field of a SETB statement or an AIF statement does not consist of valid character relational expressions, arithmetic relational expressions, and single SETB symbols, connected by logical operators.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid logical expression.

**Severity:** 12

---

### ASMA133S Illegal substring reference - xxxxxxxx

**Explanation:** A substring expression following a SETC expression does not consist of two valid SETA expressions separated by a comma and enclosed in parentheses.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid substring expression. The second value in the substring expression can be \*.

**Severity:** 12

---

### ASMA134S Invalid relational operator - xxxxxxxx

**Explanation:** Characters other than EQ, NE, LT, GT, LE, or GE are used in a SETB expression where a relational operator is expected.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid relational operator.

**Severity:** 12

---

### ASMA135S Invalid logical operator - xxxxxxxx

**Explanation:** Characters other than AND, OR, NOT, or XOR are used in a SETB expression where a logical operator is expected.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid logical operator.

**Severity:** 12

---

### ASMA136S Illegal logical/relational operator

**Explanation:** Characters other than a valid logical or relational operator were found where a logical or relational operator was expected.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid logical or relational operator.

**Severity:** 12

---

### ASMA137S Invalid character expression - xxxxxxxx

**Explanation:** The operand of a SETC statement or the character value used in a character relation is erroneous. It must be a valid type attribute (T) reference, a valid operation code attribute (O) or a valid character expression enclosed in quotation marks.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid character expression.

**Severity:** 12

---

### ASMA138W Non-empty PUSH xxxxxxxx stack

**Explanation:** The number of PUSH instructions exceeds the number of POP instructions at the end of the assembly. This indicates a potential error.

**System action:** The assembly continues.

**Programmer response:** Change your program to issue POP instructions for all PUSHes. You can suppress this warning by specifying the NOPUSH suboption of the FLAG option.

**Severity:** 4

---

### ASMA139S EOD during REPRO processing

**Explanation:** A REPRO statement was immediately followed by an end-of-data so that no valid record could be punched. The REPRO is either the last record of source input or the last record of a COPY member.

**System action:** The REPRO statement is ignored.

**Programmer response:** Remove the REPRO or ensure that it is followed by a record to be punched.

**Severity:** 12

---

### ASMA140W END record missing

**Explanation:** End-of-file on the source input data set occurred before an END statement was read. One of the following has occurred:

- The END statement was omitted or misspelled.
- The END operation code was changed or deleted by OPSYN or by definition of a macro named END. The lookahead phase of the assembler marks what it

thinks is the END statement. If an OPSYN statement or a macro definition redefines the END statement, premature end-of-input might occur because the assembler does not pass the original END statement.

**System action:** An END statement is generated. It is assigned a statement number but not printed. If any literals are waiting, they are processed as usual following the END statement.

**Programmer response:** Check for lost records. Supply a valid END statement; or, if you use OPSYN to define another symbol as END, place it *before* the possible entry into the lookahead phase.

**Severity:** 4

---

### ASMA141E Bad character in operation code - xxxxxxxx

**Explanation:** The operation code contains a non-alphanumeric character, that is, a character other than A to Z, 0 to 9, \$, #, @ or -. Embedded spaces are not allowed.

**System action:** The statement is ignored.

**Programmer response:** Supply a valid operation code. If the operation code is formed by variable symbol substitution, check the statements leading to substitution.

**Severity:** 8

---

### ASMA142E Operation code not complete on first record

**Explanation:** The whole name and operation code, including a trailing space, is not contained on the first record (before the continue column—usually column 72) of a continued statement.

**System action:** The statement is ignored.

**Programmer response:** Shorten the name, operation code, or both, or simplify the statement by using a separate SETC statement to create the name or operation code by substitution.

**Severity:** 8

---

### ASMA143E Bad character in name field - xxxxxxxx

**Explanation:** The name field contains a non-alphanumeric character, that is, a character other than A to Z, 0 to 9, \$, #, @ or -.

**System action:** If possible, the statement is processed without a name. Otherwise, it is ignored.

**Programmer response:** Put a valid symbol in the name field.

**Severity:** 8

---

### ASMA144E Begin-to-continue columns not blank - xxxxxxxx

**Explanation:** On a continuation record, one or more columns between the begin column (usually column 1) and the continue column (usually column 16) are not blank.

**System action:** The extraneous characters are ignored.

**Programmer response:** Check whether the operand started in the wrong column or whether the preceding record contained an erroneous continuation character.

**Severity:** 8

---

### ASMA145E Operator, right parenthesis, or end-of-expression expected - xxxxxxxx

**Explanation:** One of the following has occurred:

- A letter, number, equal sign, quotation mark, or undefined character occurred following a term where a right parenthesis, an operator, a comma, or a space ending the expression was expected
- In an assembler instruction, a left parenthesis followed a term

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored and another message, relative to the operation code, is issued.

**Programmer response:** Check for an omitted or misplaced operator. Subscripting is not allowed on this statement.

**Severity:** 8

---

### ASMA146E Self-defining term too long or value too large - xxxxxxxx

**Explanation:** A self-defining term is longer than 4 bytes, (8 hexadecimal digits, 32 bits, or 4 characters), or the value of a decimal self-defining term is greater than  $2^{31}-1$ .

**System action:** A machine instruction assembles as zero. An assembler instruction is ignored. However, another message, relative to the operation code, is issued.

**Programmer response:** Reduce the size of the self-defining term, or specify it in a DC statement.

**Severity:** 8

---

### ASMA147E Symbol too long, or first character not a letter - xxxxxxxx

**Explanation:** A symbol is longer than 63 characters, or does not begin with a letter, \$, #, @ or underscore (\_).

**System action:** If the symbol is in the name field, the statement is processed as unnamed. If the symbol is in the operand field, an assembler operation or a macro definition model statement is ignored and a machine

## Assembly error diagnostic messages

operation assembles as zero.

**Programmer response:** Supply a valid symbol.

**Severity:** 8

---

### ASMA148E Self-defining term lacks ending quote or has bad character - xxxxxxxx

**Explanation:** A hexadecimal or binary self-defining term contains a character that is not permitted or is missing the final quotation mark, or a pure DBCS self-defining term contains SO and SI with no double-byte data between them.

**System action:** A machine operation assembles as zero. An assembler operation is ignored and another message, relative to the operation code, is issued.

**Programmer response:** Correct the incorrect term.

**Severity:** 8

---

### ASMA149E Literal length exceeds 256 characters, including = sign - xxxxxxxx

**Explanation:** A literal is longer than 256 characters.

**System action:** The instruction assembles as zero.

**Programmer response:** Shorten the literal, or change it to a DC statement.

**Severity:** 8

---

### ASMA150E Symbol has non-alphanumeric character or invalid delimiter - xxxxxxxx

**Explanation:** The first character following a symbol is not a valid delimiter (plus sign, minus sign, asterisk, slash, left or right parenthesis, comma, or space).

**System action:** A machine operation assembles as zero. An assembler operation is ignored, and another message, relative to this operation code, is issued.

**Programmer response:** Ensure that the symbol does not contain a non-alphanumeric character and that it is followed by a valid delimiter.

**Severity:** 8

---

### ASMA151E Literal expression modifiers must be absolute and predefined - xxxxxxxx

**Explanation:** The duplication factor or length modifier in a literal is not a self-defining term, or an expression using self-defining terms or previously defined symbols.

**System action:** The statement assembles as zero.

**Programmer response:** Supply a valid self-defining term or ensure that symbols appear in the name field of a *previous* statement.

**Severity:** 8

---

### ASMA152S External symbol too long or unacceptable character - xxxxxxxx

**Explanation:** One of the following errors has occurred:

- An external symbol is longer than 8 characters, or the limit is 63 characters when the GOFF/XOBJECT option is in effect, or contains a bad character. An external symbol might be the name of a CSECT, RSECT, START, DXD, AMODE, RMODE, or COM statement, or the operand of an ENTRY, EXTRN, or WXTRN statement or a Q-type or V-type address constant.
- The operand of an ENTRY, EXTRN, or WXTRN statement or a Q-type or V-type address constant is an expression instead of a single term, or contains a bad character.
- A class name in a CATTR statement is longer than 16 characters, or contains a bad character.

**System action:** The symbol does not appear in the external symbol dictionary. If the error is in the name field, an attempt is made to process the statement as unnamed. If the error is in the operand field, the bad operand is ignored and, if possible, the following operands are processed. A bad constant assembles as zero.

**Programmer response:** Supply a shorter name or replace the expression with a symbol.

**Severity:** 12

---

### ASMA153S START statement illegal - CSECT already begun

**Explanation:** A START statement occurred after the beginning of a control section.

**System action:** The statement is processed as a CSECT statement; any operand is ignored.

**Programmer response:** Ensure that the START precedes all machine instructions and any assembler instruction, such as EQU, that initiates a control section. If you want EQU statements before the START, place them in a dummy section (DSECT).

**Severity:** 12

---

### ASMA154E Operand must be absolute, predefined symbols; set to zero - xxxxxxxx

**Explanation:** The operand on a SETA, SETB, SETC, START or MHELP statement is not correct. If there is another message with this statement, this message is advisory. If this message appears alone, it indicates one of the following:

- There is a location counter reference (\*) in a START operand.
- An expression does not consist of absolute terms, predefined symbols, or both.
- The statement is too complex. For example, it might have too many forward references or cause arithmetic overflow during evaluation.

- The statement is circularly defined.
- A relocatable term is multiplied or divided.

**System action:** The operand of the statement is treated as zero.

**Programmer response:** Correct the error if it exists. Paired relocatable symbols in different LOCTRs, even though in the same CSECT, DSECT, or RSECT, are not valid where an absolute, predefined value is required.

**Severity:** 8

### ASMA155S Previous use of symbol is not this section type

**Explanation:** The name on a CSECT, DSECT, RSECT, COM, CATTR, or LOCTR statement has been used previously, on a different type of statement. For example, the name on a CSECT has been used before on a statement other than CSECT, such as a machine instruction or a LOCTR.

**System action:** This name is ignored, and the statement processes as unnamed.

**Programmer response:** Correct the misspelled name, or change the name to one that does not conflict.

**Severity:** 12

### ASMA156S Only ordinary symbols, separated by commas, allowed

**Explanation:** The operand field of an ENTRY, EXTRN, or WXTRN statement contains a symbol that does not consist of 1-to-8 alphanumeric characters, the first being alphabetic, or the operands are not separated by a comma.

**System action:** The operand in error is ignored. If other operands follow, they process normally.

**Programmer response:** Supply a correct symbol or insert the missing comma. If you want an expression as an ENTRY statement operand (such as SYMBOL+4), use an EQU statement to define an additional symbol.

**Severity:** 12

### ASMA157S Operand must be a simply-relocatable expression

**Explanation:** If there is another message with this statement, this message is advisory. If this message appears alone, the operand of an ORG or END statement is not a simple relocatable expression, is too complex, or is circularly defined. The error might also be that the END operand symbol is not in a CSECT, or is not an external symbol without addend.

**System action:** An ORG statement or the operand of an END statement is ignored.

**Programmer response:** If an error exists, supply a correct expression. Paired relocatable symbols in

different LOCTRs, even though in the same CSECT or DSECT, might cause circular definition when used in an ORG statement.

**Severity:** 12

### ASMA158E Operand expression is defective; set to \*

**Explanation:** The first operand of an EQU statement is defective. If another message appears with this statement, this message is advisory. If this message appears alone, one of the following errors has occurred:

- The statement is too complex. For example, it has too many forward references or causes an arithmetic overflow during evaluation.
- The statement is circularly defined.
- The statement contains a relocatable term that is multiplied or divided.

**System action:** The symbol in the name field is equated to the current value of the location counter (\*), and operands 2 and 3 of the statement, if present, are ignored.

**Programmer response:** If an error exists, supply a correct expression for operand 1 of the statement.

**Severity:** 8

### ASMA159S Operand must be absolute, proper multiples of 2 or 4

**Explanation:** The combination of operands of a CNOP statement is not one of the following valid combinations:

0,4	2,4
0,8	2,8
4,8	6,8
0,16	2,16
4,16	6,16
8,16	10,16
12,16	14,16

**System action:** The statement is ignored. However, the location counter is adjusted to a halfword boundary.

**Programmer response:** Supply a valid combination of CNOP operands.

**Severity:** 12

### ASMA160W Invalid BYTE function operand xxxxxxxx

**Explanation:** The value xxxxxxxx of the operand of the BYTE built-in function is outside the expected range of 0–255.

**System action:** The low-order eight bits of the operand's value are used.

**Programmer response:** Supply an arithmetic expression which returns an acceptable value.

**Severity:** 4



## Assembly error diagnostic messages

---

### ASMA161W Only one TITLE statement may have a name field

**Explanation:** More than one TITLE statement has a name field. The named TITLE statement need not be the first one in the assembly, but it must be the only one named.

**System action:** The name on this TITLE statement is ignored. The name used for deck identification is taken from the first named TITLE statement encountered.

**Programmer response:** Delete the unwanted name.

**Severity:** 4

---

### ASMA162S PUNCH operand exceeds 80 columns; ignored

**Explanation:** A PUNCH statement attempted to punch more than 80 characters into a record.

**System action:** The statement is ignored. The record is not punched.

**Programmer response:** Shorten the operand to 80 characters or fewer or use more than one PUNCH statement.

**Severity:** 12

---

### ASMA163W Operand not properly enclosed in quotes

**Explanation:** The operand of a PUNCH or TITLE statement does not begin with a quotation mark, or the operand of a PUNCH, MNOTE, or TITLE statement does not end with a quotation mark, or the ending quotation mark is not followed by a space.

**System action:** The statement is ignored.

**Programmer response:** Supply the missing quotation mark. Be sure that a quotation mark to be punched or printed as data is represented as two quotation marks.

**Severity:** 4

---

### ASMA164W Operand is a null string - record not punched

**Explanation:** A PUNCH statement does not have any characters between its two single quotation marks, or a single quotation mark to be punched as data is not represented by two single quotation marks.

**System action:** The statement is ignored.

**Programmer response:** Correct the operand. If you want to "punch" a blank record, the operand of the PUNCH statement should be a space enclosed in single quotation marks.

**Severity:** 4

---

### ASMA165W Unexpected name field

**Explanation:** The name field on this statement is not blank and is not a sequence symbol. The name field can not be an ordinary symbol.

For example, this message is generated by the statement

```
X ANOP
```

**System action:** The name is equated to the current value of the location counter (\*). However, if no control section has been started, the name is equated to zero.

**Programmer response:** Remove the name field, or ensure the name is preceded with a period if you want it to be a sequence symbol.

**Severity:** 4

---

### ASMA166S Sequence symbol too long - xxxxxxxx

**Explanation:** A sequence symbol contains more than 62 characters following the period.

**System action:** If the sequence symbol is in the name field, the statement is processed without a name. If it is in the operand field of an AIF or AGO statement, the whole statement is ignored.

**Programmer response:** Shorten the sequence symbol.

**Severity:** 12

---

### ASMA167E Required name missing

**Explanation:** This statement requires a name and has none. The name field might be blank because an error occurred during an attempt to create the name by substitution or because a sequence symbol was used as the name.

For example, this message is generated by the statement

```
EQU 3 Empty name field
```

**System action:** The statement is ignored.

**Programmer response:** Supply a valid name or ensure that a valid name is created by substitution. If a sequence symbol is needed, put it on an ANOP statement ahead of this one and put a name on this statement. If this message is generated for a LOCTR, when attempting to continue a location counter for an unnamed section, then first supply an appropriately named LOCTR in the unnamed section so that subsequent LOCTRs can continue by specifying the name.

**Severity:** 8

---

## ASMA168C Undefined sequence symbol - xxxxxxxx

**Explanation:** The sequence symbol in the operand field of an AIF or AGO statement outside a macro definition is not defined; that is, it does not appear in the name field of an associated statement.

**System action:** This statement is ignored; assembly continues with the next statement.

**Programmer response:** If the sequence symbol is misspelled or omitted, correct it. When the sequence symbol is not previously defined, the assembler looks ahead for the definitions. The lookahead stops when an END statement or an OPSYN equivalent is encountered. Be sure that OPSYN statements and macro definitions that redefine END precede possible entry into look-ahead.

**Severity:** 16

---

## ASMA169I Implicit length of symbol *symbol* used for operand *n*

**Explanation:** A length subfield was omitted from operand *n* in an SS-format machine instruction and the implicit length of *symbol* is assembled into the object code of the instruction.

**System action:** The instruction is assembled using an implicit length which:

- For an implicit address, is the length attribute of the first or only term in the expression representing the implicit address
- For an explicit address, is the length attribute of the first or only term in the expression representing the displacement

**Programmer response:** Check the instruction to ensure that the operation and operands are coded correctly. You can suppress this warning by specifying the NOIMPLEN suboption of the FLAG option.

**Severity:** 0

---

## ASMA170S Interlude error-logging capacity exceeded

**Explanation:** The table that the interlude phase of the assembler uses to keep track of the errors it detects is full. This does not stop error detection by other phases of the assembler.

**System action:** If there are additional errors, normally detected by the interlude phase, in other statements either before or after this one, they are not flagged. Statement processing depends on the type of error.

**Programmer response:** Correct the indicated errors, and run the assembly again to diagnose any further errors.

**Severity:** 12

---

## ASMA171S Standard value too long

**Explanation:** The standard (default) value of a keyword parameter on a macro prototype statement is longer than 2014 characters.

**System action:** The parameter in error and the following parameters are ignored.

**Programmer response:** Shorten the standard value.

**Severity:** 12

---

## ASMA172E Negative duplication factor; default=1 - xxxxxxxx

**Explanation:** The duplication factor of a SETC statement is negative.

**System action:** The duplication factor is given a default value of 1.

**Programmer response:** Supply a non-negative duplication factor.

**Severity:** 8

---

## ASMA173S Delimiter error, expected blank - xxxxxxxx

**Explanation:** The character string xxxxxxxx is found where a blank (end of operand) is required.

**System action:** A machine instruction assembles as zero. An ORG statement is ignored. For an EQU or END statement, the string is ignored and the operand processes normally. For a CNOP statement, the location counter is aligned to a halfword boundary.

**Programmer response:** Insert a comma, or replace the string with a space. Look for an extra operand or a missing left parenthesis.

**Severity:** 12

---

## ASMA174S Delimiter error, expected blank or comma - xxxxxxxx

**Explanation:** The character string xxxxxxxx is found where a blank or a comma is required.

**System action:** A machine instruction assembles as zero. For a USING or DROP statement, the incorrect delimiter is ignored and the operand is processed normally.

**Programmer response:** Insert a comma, or replace the string with a space. Look for an extra operand or a missing left parenthesis.

**Severity:** 12

## Assembly error diagnostic messages

---

### ASMA175S Delimiter error, expected comma - xxxxxxxx

**Explanation:** The character string xxxxxxxx is used where a comma is required.

**System action:** A machine instruction assembles as zero. For a CNOP statement, the location counter is aligned to a halfword boundary.

**Programmer response:** Insert a comma, or replace the string with a space. Be sure each expression is syntactically correct and that no parentheses are omitted.

**Severity:** 12

---

### ASMA176E Operand 4 must be absolute, 1-4 bytes; ignored

**Explanation:** If there is another message with this statement, this message is advisory. If this message appears alone, the fourth operand of an EQU statement contains one of the following errors:

- It is not an absolute term or expression whose value is from 1 to 4 bytes in size
- It contains a symbol that is not previously defined
- It is circularly defined
- It is too complex. For example, it causes an arithmetic overflow during evaluation.

**System action:** The fourth operand is ignored, and the program type of the EQU statement is set to binary zeros.

**Programmer response:** Correct the error if it exists. Note that paired relocatable symbols in different LOCTRs, even though in the same CSECT, are not valid where an absolute, predefined value is required.

**Severity:** 8

---

### ASMA177E Operand 5 must be absolute, 1-4 bytes; ignored

**Explanation:** If there is another message with this statement, this message is advisory. If this message appears alone, the fifth operand of an EQU statement contains one of the following errors:

- It is not an absolute term or expression whose value is from 1 to 4 bytes in size.
- It contains a symbol that is not previously defined
- It is circularly defined
- It is too complex. For example, it causes an arithmetic overflow during evaluation.

**System action:** The fifth operand is ignored, and the assembler type of the EQU statement is set to spaces.

**Programmer response:** Correct the error if it exists. Note that paired relocatable symbols in different LOCTRs, even though in the same CSECT, are not valid where an absolute, predefined value is required.

**Severity:** 8

---

### ASMA178S Delimiter error, expected comma or right parenthesis - xxxxxxxx

**Explanation:** The character string xxxxxxxx is used in a machine instruction when a comma or a right parenthesis is required.

**System action:** The machine instruction assembles as zero.

**Programmer response:** Insert a comma, or replace the string with a right parenthesis. Look for a missing base field.

**Severity:** 12

---

### ASMA179S Delimiter error, expected right parenthesis - xxxxxxxx

**Explanation:** The character string xxxxxxxx is used in a machine instruction when a right parenthesis is required.

**System action:** The machine instruction assembles as zero.

**Programmer response:** Replace the string with a right parenthesis. Look for an index field used where it is not allowed.

**Severity:** 12

---

### ASMA180S Operand must be absolute

**Explanation:** The operand of a SPACE or CEJECT statement or the first, third, or fourth operand of a CCW statement is not an absolute term.

**System action:** A SPACE or CEJECT statement is ignored. A CCW statement assembles as zero.

**Programmer response:** Supply an absolute operand. Paired relocatable terms can span LOCTRs but must be in the same control section.

**Severity:** 12

---

### ASMA181S CCW operand value is outside allowable range

**Explanation:** One or more operands of a CCW statement are not within the following limits:

- 1st operand—0 to 255
- 2nd operand—0 to 16 777 215 (CCW, CCW0); or 0 to 2 147 483 647 (CCW1)
- 3rd operand—0-255 and a multiple of 8
- 4th operand—0-65 535

**System action:** The CCW assembles as zero.

**Programmer response:** Supply valid operands.

**Severity:** 12



---

### ASMA182E Operand 2 must be absolute, 0-65535; ignored

**Explanation:** If there is another message with this statement, this message is advisory. If this message appears alone, the second operand of an EQU statement contains one of the following errors:

- It is not an absolute term or expression whose value is within the range of 0 to 65,535
- It contains a symbol that is not previously defined
- It is circularly defined
- It is too complex; for example, it causes an arithmetic overflow during evaluation
- It is derived from an absolute value
- It contains an expression that cannot be fully evaluated

**System action:** Operand 2 is ignored, and the length attribute of the first operand is used. If the third operand is present, it processes normally.

**Programmer response:** Correct the error if it exists. Paired relocatable symbols in different LOCTRs, even though in the same CSECT, are not valid where an absolute, predefined value is required.

**Severity:** 8

---

### ASMA183E Operand 3 must be absolute, 0-255; ignored

**Explanation:** If there is another message with this statement, this message is advisory. If this message appears alone, the third operand of an EQU statement contains one of the following errors:

- It is not an absolute term or expression whose value is within the range of 0 to 255
- It contains a symbol that is not previously defined
- It is circularly defined
- It is too complex; for example, it causes an arithmetic overflow during evaluation.

**System action:** The third operand is ignored, and the type attribute of the EQU statement is set to U.

**Programmer response:** Correct the error if it exists. Note that paired relocatable symbols in different LOCTRs, even though in the same CSECT, are not valid where an absolute, predefined value is required.

**Severity:** 8

---

### ASMA184C COPY disaster

**Explanation:** The assembler copied a library member (processed a COPY statement) while looking ahead for attribute references. However, when the complete text was analyzed, the COPY operation code had been changed by an OPSYN statement or read by an AREAD statement, and the COPY should not have been processed. (Lookahead phase ignores OPSYN statements.) This message follows the first record of the COPY code.

**System action:** The library member assembles. If it included an ICTL statement, the format of that ICTL is used.

**Programmer response:** Move COPY statements, or OPSYN statements that modify the meaning of COPY, to a point in the assembly before the entry into lookahead mode (that is, prior to ASMA006I Lookahead invoked).

**Severity:** 16

---

### ASMA185W Operand 2 is erroneous - xxxxxxxx

**Explanation:** The second operand is incorrect, or two operands appear where there should be only one.

**System action:** The second operand is ignored.

**Programmer response:** Remove or correct the second operand.

**Severity:** 4

---

### ASMA186E AMODE/RMODE already set for this ESD item

**Explanation:** A previous AMODE instruction has the same name field as this AMODE instruction, or a previous RMODE instruction has the same name field as this RMODE instruction.

**System action:** The instruction in error is ignored.

**Programmer response:** Remove the conflicting instruction or specify the name of another control section.

**Severity:** 8

---

### ASMA187E The name field is invalid - xxxxxxxx

**Explanation:** The name field of an AMODE, RMODE or XATTR instruction is invalid. The name field must be one of the following:

- A valid control section name
- An ENTRY name (for AMODE or XATTR with the GOFF option set)
- A valid external name (XATTR only)

If the XATTR statement uses the PSECT operand then the name field must specify either a valid control section name or ENTRY name.

**System action:** The instruction in error is ignored, and the name does not appear in the cross-reference listing.

**Programmer response:** Specify a valid name and resubmit the assembly.

**Severity:** 8

## Assembly error diagnostic messages

---

### ASMA188E Incompatible AMODE and RMODE attributes

**Explanation:** A previous AMODE 24 instruction has the same name field as this RMODE ANY instruction, or a previous RMODE ANY instruction has the same name field as this AMODE 24 instruction.

**System action:** The instruction in error is ignored.

**Programmer response:** Change the AMODE and RMODE attributes so they are no longer incompatible. All combinations except AMODE 24 and RMODE ANY are valid.

**Severity:** 8

---

### ASMA189E OPSYN not permitted for REPRO

**Explanation:** REPRO is specified in either the name field or the operand field of an OPSYN instruction, but a REPRO statement has been previously encountered in the source module. Once a REPRO statement has been encountered, the REPRO symbolic operation code cannot be redefined using the OPSYN instruction.

**System action:** The OPSYN instruction is ignored.

**Programmer response:** Remove the OPSYN instruction, or remove the previously encountered REPRO statement.

**Severity:** 8

---

### ASMA190E CATTR instruction invalid because no executable section started

**Explanation:** A CATTR instruction must be preceded by a CSECT, START, or RSECT instruction.

**System action:** The CATTR instruction is ignored.

**Programmer response:** Remove the CATTR instruction, or precede it with a CSECT, START, or RSECT instruction.

**Severity:** 8

---

### ASMA191W CATTR instruction operands ignored

**Explanation:** You specified operands on a CATTR instruction which has the same class name as a previous CATTR instruction.

**System action:** The assembler ignores the operands, and continues as if you did not specify any operands.

**Programmer response:** You can correct this error by:

- Removing the operands from the CATTR instruction in error
- Changing the class name for the CATTR instruction in error
- Removing the CATTR instruction in error

**Severity:** 4

---

### ASMA192W Lost precision - underflow to zero

**Explanation:** The value supplied is non-zero and is too small to be represented.

**System action:** The constant assembles with an exponent and fraction of zero.

**Programmer response:** Supply a larger value or a longer constant type.

**Severity:** 4

---

### ASMA193W Lost precision - underflow to denormal

**Explanation:** The value supplied is non-zero and is too small to be represented in normalized form, but can be represented in denormalized form.

**System action:** The constant assembles with the denormalized form.

**Programmer response:** Supply a larger value or a longer constant type,

**Severity:** 4

---

### ASMA194W Nominal value too large - overflow to MAX

**Explanation:** The value supplied is too large to be represented and the rounding mode of the constant indicates rounding towards zero. The value is represented as the signed maximum representable value.

**System action:** The constant assembles with the signed maximum value.

**Programmer response:** Supply a smaller value or a longer constant type.

**Severity:** 4

---

### ASMA195W Nominal value too large - overflow to INF

**Explanation:** The value supplied is too large to be represented and the rounding mode of the constant indicates rounding away from zero. The value is represented as a signed infinity.

**System action:** The constant assembles with the signed special value INF.

**Programmer response:** Supply a smaller value or a longer constant type.

**Severity:** 4

---

### ASMA196W Scaling modifier ignored for binary floating-point constant

**Explanation:** A scaling modifier has been included in the definition of a binary floating-point constant.

**System action:** The scaling modifier has been ignored.

**Programmer response:** Remove the scale modifier.

**Severity:** 4

---

**ASMA198E Exponent modifier is not permitted for special value**

**Explanation:** The exponent modifier is not permitted for a floating-point special value.

**System action:** The constant assembles as zeros.

**Programmer response:** Remove the exponent modifier.

**Severity:** 8

---

**ASMA199E Rounding indicator invalid**

**Explanation:** The rounding indicator for the floating-point constant is not a valid value.

**System action:** The operand in error and the following operands are ignored.

**Programmer response:** Correct the rounding indicator.

**Severity:** 8

---

**ASMA201W SO or SI in continuation column - no continuation assumed**

**Explanation:** When High Level Assembler is invoked with the DBCS option, the double-byte delimiters SO and SI are treated as spaces in the continuation indicator field, and *not* as continuation indicators.

**System action:** The SO or SI in the continuation indicator field assembles as a space, and the next line is not treated as a continuation line.

**Programmer response:** If continuation is required, then rearrange the source line so that a non-space EBCDIC character can be used to indicate continuation. If continuation is not required, check that everything preceding the SO or SI is complete and valid data.

**Severity:** 4

---

**ASMA202W Shift-in not found at extended continuation; check data truncation - xxxxxxxx**

**Explanation:** The assembler has detected an extended continuation indicator that is not on a source statement containing double-byte data. The extended continuation indicator feature is provided to permit continuation of double-byte data, and single-byte data adjacent to double-byte data. If you use extended continuation indicators anywhere else, the assembler issues this message. As this situation can be caused by a coding error, the assembler might unintentionally treat the data as extended continuation indicators.

**System action:** The extended continuation indicators do not assemble as part of the operand.

**Programmer response:** Change the continuation indicator if unintentional truncation occurred.

**Severity:** 4

---

**ASMA203E Unbalanced double-byte delimiters - xxxxxxxx**

**Explanation:** A mismatched SO or SI has been found. This could be the result of truncated or nested double-byte data. This error does NOT occur because valid double-byte data is truncated to fit within the explicit length specified for C-type DC, DS, and DXD statements and literals - that condition produces error ASMA208E.

**System action:** The operand in error, and the following operands are ignored.

**Programmer response:** Correct the incorrect double-byte data.

**Severity:** 8

---

**ASMA204E Invalid double-byte data - xxxxxxxx**

**Explanation:** All data between SO and SI must be valid double-byte characters. A valid double-byte character is defined as either double-byte space (X'4040'), or two bytes each of which must be in the range X'41' to X'FE' inclusive.

This error does not apply to the operands of macro instructions.

**System action:** The operand in error, and the following operands are ignored.

**Programmer response:** Correct the incorrect double-byte data.

**Severity:** 8

---

**ASMA205E Extended continuation end column must not extend into continue column**

**Explanation:** The extended continuation indicator extended into the continue column.

**System action:** The extended continuation indicator is ignored. The following record or records might be treated as incorrect. The extended continuation indicators are treated as part of the source statement.

**Programmer response:** If the data in the extended continuation is to be regarded as valid input then another non-space character must be used in the continuation indication column to identify the data as valid and to continue to the next record. If the data is not to be part of the constant then remove the characters of the extended continuation and add the correct data to the continue record to the point where the extended continuation is needed. This message might be encountered when converting code that assembled with the NODBCS option to code that is to

## Assembly error diagnostic messages

be assembled with the DBCS option.

**Severity:** 8

---

### ASMA206E G-type constant must not contain single-byte data - xxxxxxxx

**Explanation:** A G-type constant or self-defining term, after substitution has occurred, must consist entirely of double-byte data, correctly delimited by SO and SI. If SO or SI are found in any byte position other than the first and last respectively (excepting redundant SI/SO pairs which are removed) then this error is reported.

**System action:** The operand in error, and the following operands are ignored.

**Programmer response:** Either remove the single-byte data from the operand, or change the constant to a C-type.

**Severity:** 8

---

### ASMA207E Length of G-type constant must be a multiple of 2 - xxxxxxxx

**Explanation:** A G-type constant must contain only double-byte data. If assembled with a length modifier which is not a multiple of 2, incorrect double-byte data is created.

**System action:** The operand in error, and the operands following are ignored.

**Programmer response:** Either correct the length modifier, or change the constant to a C-type.

**Severity:** 8

---

### ASMA208E Truncation into double-byte data is not permitted - xxxxxxxx

**Explanation:** The explicit length of a C-type constant in a DS, DC or DXD statement or literal must not cause the nominal value to be truncated at any point within double-byte data.

**System action:** The operand in error, and the following operands are ignored.

**Programmer response:** Either correct the length modifier, or change the double-byte data so that it is not truncated.

**Severity:** 8

---

### ASMA209E Symbol not name of class, DXD or DSECT

**Explanation:** The operand of a J-type address constant is not the name of a class, DXD, or DSECT.

**System action:** The constant assembles as zero.

**Programmer response:** Supply a valid operand.

**Severity:** 8

---

### ASMA210E Illegal register usage

**Explanation:** The register operands for the machine instruction must be unique.

**System action:** The machine instruction assembles as zero.

**Programmer response:** Correct the instruction such that the operands specified are unique.

**Severity:** 8

---

### ASMA211E Unicode conversion table not available.

**Explanation:** The address of the UNICODE conversion table is zero in the Code Page module specified in the CODEPAGE option.

**System action:** The constant is not converted.

**Programmer response:** Ensure the code page module is generated according to the instructions described in Appendix M, "How to generate a Unicode translation table," on page 409.

**Severity:** 12

---

### ASMA212W Branch address alignment for xxxxxxxx unfavorable

**Explanation:** A branch address referenced by this statement might not be aligned to the required boundary for this instruction; for example, the target referenced by a Branch and Save (BAS) instruction might not be aligned on a halfword boundary.

**System action:** The instruction assembles as written.

**Programmer response:** Correct the operand if it is in error. To suppress this message, use the FLAG(NOALIGN) assembler option.

**Severity:** 4

---

### ASMA213W Storage alignment for xxxxxxxx unfavorable

**Explanation:** An address referenced by this statement might not be aligned to the required boundary for this instruction; for example, the data referenced by a Compare and Swap (CS) instruction might not be aligned on a fullword boundary.

**System action:** The instruction assembles as written.

**Programmer response:** Correct the operand if it is in error. To suppress this message, use the FLAG(NOALIGN) assembler option, or specify a previous ACONTROL FLAG(NOALIGN) instruction.

**Severity:** 4

---

### ASMA214E Invalid operand value - *&var*

**Explanation:** The contents of operand *&var* is invalid for one of the following reasons:

- null value
- a hexadecimal value is required in the operand of a hexadecimal conversion function
- a binary value is required in the operand of a binary conversion function
- the operand is longer than the function supports
- A decimal value is required in the operand of a decimal conversion function
- The operand is outside the range of acceptable values that the function supports

**System action:** The statement is ignored.

**Programmer response:** Supply a valid operand value.

**Severity:** 8

---

### ASMA215W Relative Immediate external relocation in NOGOFF object text - *xxxxxxx*

**Explanation:** The external address *xxxxxxx* is used in a relative immediate branch instruction and the assembly is using the old object text format.

**System action:** A special RLD entry is created.

**Programmer response:** Check that the linkage editor/binder is able to process the RLD entry. On z/VM and z/VSE systems, check that the system loader and linker can support relative-external relocation types before using them.

**Severity:** 4

---

### ASMA216W Quad-word alignment in NOGOFF object text

**Explanation:** The SECTALGN option has been used to request that sections are aligned on quad word boundaries with the NOGOFF option.

**System action:** None - the ESD entries are created as requested.

**Programmer response:** Check that the linkage editor/binder is able to process the updated ESD entries.

**Severity:** 4

---

### ASMA217W DFP lower clamped to zero - *xxxxxxx*

**Explanation:** The Decimal Floating Point conversion routine has had to modify (or clamp) the exponent in order to fit within the format. No significant digits have been lost.

**System action:** The constant assembles with the correct value using the clamped exponent.

**Programmer response:** Modify the exponent value to remove the need for clamping.

**Severity:** 4

---

### ASMA218W DFP upper clamped to zero - *xxxxxxx*

**Explanation:** The Decimal Floating Point conversion routine has had to modify (or clamp) the exponent in order to fit within the format. No significant digits have been lost.

**System action:** The constant assembles with the correct value using the clamped exponent.

**Programmer response:** Modify the exponent value to remove the need for clamping.

**Severity:** 4

---

### ASMA219W DFP lower clamped non zero - *xxxxxxx*

**Explanation:** The Decimal Floating Point conversion routine has had to modify (or clamp) the exponent in order to fit within the format. No significant digits have been lost.

**System action:** The constant assembles with the correct value using the clamped exponent.

**Programmer response:** Modify the exponent value to remove the need for clamping.

**Severity:** 4

---

### ASMA220W DFP upper clamped non zero - *xxxxxxx*

**Explanation:** The Decimal Floating Point conversion routine has had to modify (or clamp) the exponent in order to fit within the format. No significant digits have been lost.

**System action:** The constant assembles with the correct value using the clamped exponent.

**Programmer response:** Modify the exponent value to remove the need for clamping.

**Severity:** 4

---

### ASMA253C Too many errors

**Explanation:** No more error messages can be issued for this statement, because the assembler work area in which the errors are reported is full.

**System action:** If more errors are detected for this statement, the messages, annotated text, or both, are discarded.

**Programmer response:** Correct the indicated errors, and rerun the assembly. If there are more errors on this statement, they will be detected in the next assembly.

**Severity:** 16



## Assembly error diagnostic messages

---

### ASMA254I \*\*\* MNOTE \*\*\*

**Explanation:** The text of an MNOTE statement, which is appended to this message, has been generated by your program or by a macro definition or a library member copied into your program. An MNOTE statement enables a source program or a macro definition to signal the assembler to generate an error or informational message.

**System action:** None.

**Programmer response:** Investigate the reason for the MNOTE. Errors flagged by MNOTE often cause the program to fail if it is run.

**Severity:** An MNOTE is assigned a severity code of 0 to 255 by the writer of the MNOTE statement.

---

### ASMA300W USING overridden by a prior active USING on statement number *nnnnnn*

**Explanation:** The USING instruction specifies the same base address as a previous USING instruction at statement number *nnnnnn*, and the base register specified is lower-numbered than the previously specified base register.

**System action:** The assembler uses the higher-numbered base register for address resolution of symbolic addresses within the USING range.

**Programmer response:** Check your USING statements to ensure that you have specified the correct base address and base register and that you have not omitted a needed DROP statement for the previous base register. You can suppress this message by reducing the value specified in the WARN sub-option of the USING option by 1.

**Severity:** 4

---

### ASMA301W Prior active USING on statement number *nnnnnn* overridden by this USING

**Explanation:** The USING instruction specifies the same base address as a previous USING instruction at statement number *nnnnnn*, and the base register specified is higher-numbered than the previous base register.

**System action:** The assembler uses the higher-numbered base register for address resolution of symbolic addresses within the USING range.

**Programmer response:** Check your USING statements to ensure that you have specified the correct base address and base register and that you have not omitted a needed DROP statement for the previous base register. You can suppress this message by reducing the value specified in the WARN sub-option of the USING option by 1.

**Severity:** 4

---

### ASMA302W USING specifies register 0 with a non-zero absolute or relocatable base address

**Explanation:** The assembler assumes that when register 0 is used as a base register, it contains zero. Therefore, regardless of the value specified for the base address, displacements are calculated from base 0.

**System action:** The assembler calculates displacements as if the base address specified were absolute or relocatable zero.

**Programmer response:** Check the USING statement to ensure you have specified the correct base address and base register. You can suppress this message by reducing the value specified in the WARN suboption of the USING option by 2.

**Severity:** 4

---

### ASMA303W Multiple address resolutions may result from this USING and the USING on statement number *nnnnnn*

**Explanation:** The USING instruction specifies a base address that lies within the range of an earlier USING instruction at statement number *nnnnnn*. The assembler might use multiple base registers when resolving implicit addresses within the range overlap.

**System action:** The assembler computes displacements from the base address that gives the smallest displacement, and uses the corresponding base register when it assembles addresses within the range overlap.

**Programmer response:** Check your USING instructions for unintentional USING range overlaps and check that you have not omitted a needed DROP statement. You can suppress this message by reducing the value specified in the WARN suboption of the USING option by 4.

**Severity:** 4

---

### ASMA304W Displacement exceeds LIMIT value specified

**Explanation:** The address referred to by this statement has a valid displacement that is higher than the displacement limit specified in the USING(LIMIT(*xxx*)) option.

**System action:** The instruction assembles correctly.

**Programmer response:** This error diagnostic message is issued at your request. You can suppress this message by reducing the value specified in the WARN suboption of the USING option by 8.

**Severity:** 4

---

**ASMA305E Operand 1 does not refer to location within reference control section**

**Explanation:** The first operand in a dependent USING statement does not refer to a location within a reference control section defined by a DSECT, DXD, or COM instruction.

**System action:** The USING statement is ignored.

**Programmer response:** Change the USING statement to specify a location within a reference control section.

**Severity:** 8

---

**ASMA306W USING range overlaps implicit USING 0,0**

**Explanation:** The USING range overlaps the assembler's implicit USING 0,0. This implicit USING is used to convert absolute implicit addresses in the range 0 to 4095. As a result of this USING, the assembler may not generate the expected object code.

**System action:** The assembly continues

**Programmer response:** Correct the USING statement. If you believe it is correct, specify the FLAG(NOUSING0) option or a preceding ACONTROL FLAG(NOUSING0) instruction.

**Severity:** 4

---

**ASMA307E No active USING for operand *n***

**Explanation:** The operand specified occurs in a section without an active USING.

**System action:** The instruction assembles as zero.

**Programmer response:** Provide a USING instruction.

**Severity:** 8

---

**ASMA308E Repeated register *reg* nullifies prior USING range**

**Explanation:** The repeated register nullifies the range specified by a prior use of that register on the same USING instruction.

**System action:** The statement is ignored.

**Programmer response:** Correct the USING instruction.

**Severity:** 8

---

**ASMA309W Operand *xxxxxxx* resolved to a displacement with no base register**

**Explanation:** The machine instruction specifies an operand which is resolved to a baseless address when a base and displacement are expected. This might be the programmer's intent, but will usually be an error.

**System action:** Base register zero is assembled into the object code of the instruction.

**Programmer response:** Check the instruction to ensure that the operation and operands are coded correctly. If you want to reference *page zero* you can specify a USING for the appropriate DSECT with a zero base register. You can suppress this warning by specifying the NOPAGE0 suboption of the FLAG option.

**Severity:** 4

---

**ASMA310W Name already used in prior ALIAS or XATTR - *xxxxxxx***

**Explanation:** The name specified in the ALIAS or XATTR statement has already been used in a previous ALIAS or XATTR statement.

**System action:** The statement is ignored.

**Programmer response:** Change the program so that the name is used in only one ALIAS or XATTR statement.

**Severity:** 4

---

**ASMA311E Illegal ALIAS string**

**Explanation:** The ALIAS string is illegal for one of the following reasons:

- The string is null
- The string is not in the form C"ccccccc" or X'hhhhhhh'
- The string is in the form X'hhhhhhh' but an odd number of hexadecimal digits has been specified
- The string contains a character outside the valid range of X'42' to X'FE'
- The string has been used in the name entry on a previous CSECT, DSECT, RSECT, COM or LOCTR instruction

**System action:** The statement is ignored.

**Programmer response:** Change the program so that the string conforms to the required syntax.

**Severity:** 8

---

**ASMA312E ALIAS name is not declared as an external symbol - *xxxxxxx***

**Explanation:** The name specified on the ALIAS statement is not declared as an external symbol, either explicitly via an EXTRN, CSECT, RSECT, etc., or implicitly via a V-type constant.

**System action:** The statement is ignored.

**Programmer response:** Change the program so that the name is declared as an external symbol.

**Severity:** 8

## Assembly error diagnostic messages

---

### ASMA313E The end value specified in the USING is less than or equal to the base value

**Explanation:** The end value specified is less than or equal to the base value which would result in a zero or negative range.

**System action:** The end value is ignored and the default range value is used.

**Programmer response:** Change the USING statement to specify an end value that is greater than the base value.

**Severity:** 8

---

### ASMA314E The base and end values have differing relocation attributes

**Explanation:** The base and end values have differing relocation attributes; that is, they are defined in different sections.

**System action:** The end value is ignored and the default range value is used.

**Programmer response:** Change the USING statement to specify an end value that is in the same section as the base value.

**Severity:** 8

---

### ASMA315E XATTR instruction invalid when NOGOFF specified

**Explanation:** The XATTR instruction can only be used when the GOFF option is set.

**System action:** The statement is ignored.

**Programmer response:** Either remove the XATTR statement and resubmit the assembly or ensure that the GOFF option is set and resubmit the assembly.

**Severity:** 8

---

### ASMA316E Invalid PSECT symbol - *nnnnnnnn*

**Explanation:** The symbol *nnnnnnnn* specified in the PSECT operand is invalid for one of the following reasons:

- The name is undefined
- The name is a class name
- The name is not one of the following:
  - A valid control section name
  - A valid ENTRY name
  - A valid DXD name

**System action:** The PSECT operand is ignored.

**Programmer response:** Correct the PSECT operand and resubmit the assembly.

**Severity:** 8

---

### ASMA317E Invalid ATTR symbol - *nnnnnnnn*

**Explanation:** The symbol *nnnnnnnn* specified in the ATTR operand is invalid for one of the following reasons:

- The name is undefined
- The name is a DSECT name
- The name is a qualifier name

**System action:** The ATTR operand is ignored.

**Programmer response:** Correct the ATTR operand and resubmit the assembly.

**Severity:** 8

---

### ASMA318W Invalid message *n* specified for SUPRWARN option. Message ignored.

**Explanation:** Message *n*, specified as a sub-option of option SUPRWARN, is not a valid High Level Assembler message. Message ignored.

**System action:** The specified message *n* is ignored.

**Programmer response:** Change the value *n* to a valid message, or remove it from option SUPRWARN.

**Severity:** 4

---

### ASMA319W Message *n* specified for SUPRWARN option, but severity is too high. Message ignored.

**Explanation:** Message *n* specified as a sub-option of option SUPRWARN is a valid High Level Assembler message, but the severity code of message *n* is higher than allowed by option SUPRWARN.

**System action:** The specified message *n* is ignored.

**Programmer response:** Change the value *n* to a valid message, or remove it from option SUPRWARN.

**Severity:** 4

---

### ASMA320W Immediate field operand may have incorrect sign or magnitude

**Explanation:** The value of a signed immediate operand of a machine instruction is beyond the allowed range for the instruction, where the normal allowed range of values for a 16-bit signed immediate operand is -32768 through to 32767, and for a 32-bit signed immediate operand is -2147483648 through to 2147483647. Immediate operands used in an arithmetic context are signed, with bit 0 of the immediate field being used to hold the sign bit. This reduces by one the number of bits available to hold the absolute value of the operand; for example:

AHI r1,-30000 is valid, but



**AHI r1,50000** is not because bits 1-15 of the immediate field can only hold a maximum absolute value of 32767.

**System action:** The required number of low-order bits of the operand's value are used.

**Programmer response:** Use a valid immediate operand, or specify the immediate information in a DC statement or a literal and change the statement to a non-immediate type. You can suppress this message by specifying the TYPECHECK(NOMAGNITUDE) option.

**Severity:** 4

---

### ASMA321E Invalid assembler type - xxx

**Explanation:** The fifth operand of an EQU statement contains an operand that does not match the allowed assembler type values.

**System action:** The fifth operand is ignored, and the assembler type of the EQU statement is set to spaces.

**Programmer response:** Supply a valid assembler type.

**Severity:** 8

---

### ASMA322E Program type error - xxxxxxx

**Explanation:** The program type subfield on a DC or DS assembler instruction contains one of the following errors:

- It is not an absolute term or expression whose value is from 1 to 4 bytes in size.
- It contains a symbol that is not previously defined
- It is circularly defined
- It is too complex; for example, it causes an arithmetic overflow during evaluation.

**System action:** The program type subfield is ignored, and the program type of the DC statement is set to binary zeros.

**Programmer response:** Correct the error if it exists. Note that paired relocatable symbols in different LOCTRs, even though in the same CSECT, are not valid where an absolute, predefined value is required.

**Severity:** 8

---

### ASMA323W Symbol xxxxxxx has incompatible type with yyyyyyyy register field

**Explanation:** A symbol was used to provide an absolute value for a register field in a machine instruction, but the assembler type assigned to the symbol does not match the expected register type for the instruction.

**System action:** The register value is used and the object code is generated. Execution of the code will not be affected by this message.

**Programmer response:** Use a symbol with the correct assembler type. If the symbol was defined using the

EQU assembler instruction, then the assembler type is assigned to the symbol using the fifth operand. This message can be suppressed using the TYPECHECK(NOREGISTER) assembler option.

**Severity:** 4

---

### ASMA324I Symbol xxxxxxx may have incompatible type with yyyyyyyy register field

**Explanation:** A symbol was used to provide an absolute value for a register field in a machine instruction, but the assembler type assigned to the symbol does not appear to match the expected register type for the instruction. Once the assembler detects the definition of a symbol with a particular assembler type, within the current piece of source code, it uses this message to highlight apparent inconsistent use of that assembler type on machine instructions.

**System action:** The register value is used and the object code is generated. Execution of the code will not be affected by this message.

**Programmer response:** Use a symbol with the correct assembler type. If the symbol was defined using the EQU assembler instruction, then the assembler type is assigned to the symbol using the fifth operand. This message can be suppressed using the TYPECHECK(NOREGISTER) assembler option.

**Severity:** 0

---

### ASMA400W Error in invocation parameter - xxxxxxx

**Explanation:** The parameter xxxxxxx is not a recognized assembler option, or is incorrectly specified.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues, using the installation default value for the erroneously specified option.

**Programmer response:** Correct the parameter error and resubmit the assembly.

**Severity:** 4

---

### ASMA401N Fixed option cannot be overridden by invocation parameter - xxxxxxx

**Explanation:** The parameter xxxxxxx cannot be specified in the ASMAOPT file or as an invocation parameter because the option it is attempting to override was fixed when High Level Assembler was installed.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues, using the installation default value for the erroneously specified option.

## Assembly error diagnostic messages

**Programmer response:** Correct the parameter error and resubmit the assembly.

**Severity:** 2

---

### ASMA402W Invalid print line length *xxxxxx* returned by LISTING exit; exit processing bypassed

**Explanation:** When invoked with an OPEN request, the LISTING exit specified a print line length that was either outside the range 121 to 255 (z/OS and CMS), 121 to 133 (z/VSE), or was not permitted for the device to which the listing file is assigned.

**System action:** The assembler bypasses the exit when processing listing records, and writes the assembly listing to the standard listing file. The print line length is determined by the assembler.

**Programmer response:** Correct the error in the LISTING exit.

**Severity:** 4

---

### ASMA404W Invalid term line length *xxxxxx* returned by TERM exit; exit processing bypassed

**Explanation:** When invoked with an OPEN request, the TERM exit specified a line length that was either zero or greater than 255 (z/OS and CMS), 125 (z/VSE), or was not permitted for the device to which the terminal file is assigned.

**System action:** The assembler bypasses the exit when processing terminal records, and writes the terminal records to the standard terminal file. The line length is determined by the assembler.

**Programmer response:** Correct the error in the TERM exit.

**Severity:** 4

---

### ASMA409I Unable to load ASMAININFO

**Explanation:** The assembler attempted to load the INFO option module ASMAININFO, but the load failed.

**System action:** The assembly continues without listing the INFO requested.

**Programmer response:** Check that ASMAININFO is in a library accessible by the assembler.

**Severity:** 0

---

### ASMA413C Unable to open INPUT file

**Explanation:** The assembler encountered an error when attempting to open the assembler input file. This is usually caused by a job control language error.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check the JCL for the input file.

**Severity:** 16

---

### ASMA414C Unable to open LISTING file

**Explanation:** The assembler encountered an error when attempting to open the assembler listing file. This is usually caused by a job control language error.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check the JCL for the listing file.

**Severity:** 16

---

### ASMA415N Unable to open TERM file

**Explanation:** The assembler encountered an error when attempting to open the assembler terminal output file. This is usually caused by a job control language error.

**System action:** The assembly continues and no terminal file is produced.

**Programmer response:** Check the JCL for the terminal output file.

**Severity:** 2

---

### ASMA416C Unable to open DECK file

**Explanation:** The assembler encountered an error when attempting to open the assembler deck output file. This is usually caused by a job control language error.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check the JCL for the deck output file.

**Severity:** 16

---

### ASMA417C Unable to open OBJECT file

**Explanation:** The assembler encountered an error when attempting to open the assembler object output file. This is usually caused by a job control language error.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check the JCL for the object output file.

**Severity:** 16

---

## ASMA418C Unable to open ADATA file

**Explanation:** The assembler encountered an error when attempting to open the associated data file. This is usually caused by a job control language error.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check the JCL for the SYSADATA ddname (z/OS and CMS), or the SYSADAT file (z/VSE).

**Severity:** 16

---

## ASMA419C Unable to open TRACE file

**Explanation:** The assembler encountered an error when attempting to open the internal trace file. This is usually caused by a job control language error.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check the JCL for the SYSTRACE ddname (z/OS and CMS), or the SYSTRAC file (z/VSE).

**Severity:** 16

---

## ASMA420N Error in a \*PROCESS statement parameter - xxxxxxxx

**Explanation:** The parameter xxxxxxxx is not a recognized assembler option, or is incorrectly specified.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues, using the installation default value or the invocation parameter value for the erroneously specified option.

**Programmer response:** Correct the parameter error and resubmit the assembly.

**Severity:** 2

---

## ASMA421N Fixed option cannot be overridden by \*PROCESS statement parameter - xxxxxxxx

**Explanation:** The parameter xxxxxxxx cannot be specified in a \*PROCESS statement parameter because the option it is attempting to override was fixed when High Level Assembler was installed.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues, using the installation default value for the erroneously specified option.

**Programmer response:** Remove the option from the \*PROCESS statement and resubmit the assembly.

**Severity:** 2

---

## ASMA422N Option xxxxxxxx is not valid in a \*PROCESS statement

**Explanation:** The following options cannot be specified in a \*PROCESS statement:

ADATA NOADATA	OBJECT NOOBJECT
ASA NOASA	SIZE
DECK NODECK	SYSPARM
EXIT NOEXIT	TERM NOTERM
GOFF NOGOFF	TRANSLATE NOTRANSLATE
LANGUAGE	XOBJECT NOXOBJECT
LINECOUNT	
LIST NOLIST	

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues, using the installation default value or the invocation parameter value for the erroneously specified option.

**Programmer response:** Remove the option from the \*PROCESS statement and resubmit the assembly.

**Severity:** 2

---

## ASMA423N Option yyyyyyyyyy in a \*PROCESS OVERRIDE statement conflicts with an invocation or default option. Option is not permitted in \*PROCESS statement and has been ignored.

**Explanation:** The option yyyyyyyyyy specified in a \*PROCESS OVERRIDE statement conflicts with an invocation or default option. The option is not permitted in a \*PROCESS statement and has been ignored.

**System action:** If installation option PESTOP is specified, the assembler stops. If installation option NOPESTOP is specified, the assembly continues using the invocation or default option.

**Programmer response:** Correct the \*PROCESS OVERRIDE statement and resubmit the assembly.

**Severity:** 2

---

## ASMA424W Continuation column is not blank. \*PROCESS statements may not be continued.

**Explanation:** The continuation indicator field (usually column 72) is not blank for a \*PROCESS statement. \*PROCESS statements can not be continued.

**System action:** If option PESTOP is specified, the assembly stops. If option NOPESTOP is specified, the assembly continues and processes the options specified.

**Programmer response:** Recode the \*PROCESS statement, leaving the continuation column blank. If you need to specify more options that can fit on the \*PROCESS statement, add another \*PROCESS statement to your code. You can specify a maximum of 10 \*PROCESS statements.

---

## Assembly error diagnostic messages

Severity: 4

---

**ASMA425N** Option conflict in invocation parameters. *yyyyyyyyy* overrides an earlier setting.

**Explanation:** The option *yyyyyyyyy* specified as an invocation parameter in either the ASMAOPT file or the invocation parameters overrides an earlier setting of the option in either the same ASMAOPT file or the invocation parameters.

**System action:** If installation option PESTOP is specified, the assembler stops. If installation option NOPESTOP is specified, the assembly continues using the last specified conflicting option.

**Programmer response:** Correct the ASMAOPT file or the invocation parameter and resubmit the assembly.

Severity: 2

---

**ASMA426N** Option conflict in \*PROCESS statements. *yyyyyyyyy* overrides an earlier setting.

**Explanation:** The option *yyyyyyyyy* specified in a \*PROCESS statement overrides an earlier setting of the option on the same statement or a previous \*PROCESS statement.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues using the last conflicting option encountered.

**Programmer response:** Correct the \*PROCESS statement error and resubmit the assembly.

Severity: 2

---

**ASMA427N** Invocation parameter option *xxxxxxx* ignored. This option is not valid under z/VSE.

**Explanation:** The option *xxxxxxx* specified in an invocation parameter is not valid for the z/VSE operating system.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues and the option is ignored.

**Programmer response:** Remove the option from the invocation parameter and resubmit the assembly.

Severity: 2

---

**ASMA428N** \*PROCESS statement option *xxxxxxx* ignored. This option is not valid under z/VSE.

**Explanation:** The option *xxxxxxx* specified in a

\*PROCESS statement is not valid for the z/VSE operating system.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues and the option is ignored.

**Programmer response:** Remove the option from the \*PROCESS statement and resubmit the assembly.

Severity: 2

---

**ASMA429W** SYSPRINT LRECL should be at least 133 when GOFF/XOBJECT option is specified

**Explanation:** The GOFF or XOBJECT assembler option has been specified, however the logical record length of the listing file, SYSPRINT, is less than 133.

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues, however the lines in the *source and object* section are truncated.

**Programmer response:** Specify a record length of at least 133 for SYSPRINT.

Severity: 4

---

**ASMA430W** Continuation statement does not start in continue column.

**Explanation:** The operand on the continued record ends with a comma and a continuation statement is present but the continue column is blank. The continue column is column 16, unless you redefined it with an ICTL instruction.

**System action:** Any remaining continuation lines belonging to this statement are ignored.

**Programmer response:** Check that the continuation was coded as intended.

Severity: 4

---

**ASMA431W** Continuation statement may be in error - continuation indicator column is blank.

**Explanation:** A list of one or more operands ends with a comma, but the continuation indicator column is blank. The continuation indicator column is column 72, unless you redefined it with an ICTL instruction.

**System action:** The next statement assembles as a standard assembler source statement.

**Programmer response:** Check that the continuation was coded as intended.

Severity: 4

---

**ASMA432W Continuation statement may be in error - comma omitted from continued statement.**

**Explanation:** The continuation record starts in the continue column (usually column 16) but there is no comma present following the operands on the previous record.

**System action:** Any remaining continuation lines belonging to this statement are ignored.

**Programmer response:** Check that the continuation was coded as intended.

**Severity:** 4

---

**ASMA433W Statement not continued - continuation statement may be in error**

**Explanation:** The continued record is full but the continuation record does not start in the continue column (usually column 16).

**System action:** Any remaining continuation lines belonging to this statement are ignored.

**Programmer response:** Check that the continuation was coded as intended.

**Severity:** 4

---

**ASMA434N GOFF/XOBJECT option specified, option LIST(133) will be used**

**Explanation:** You specified the GOFF or XOBJECT option, and the LIST suboption is 121.

**System action:** The assembler sets the LIST suboption to 133. If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues.

**Programmer response:** To prevent this warning message, run the assembly again specifying GOFF and LIST(133).

**Severity:** 2

---

**ASMA435I Record *n* in xxxxxxxx on volume: vvvvvv**

**Explanation:** The data set xxxxxxxx which is located on volume serial vvvvvv, contains an error on record number *n*. The volume serial might not be available.

For an AINSERT instruction:

*n* The number of the statement within the AINSERT internal buffer. This number may not reflect the statement's relative statement number within the buffer at the point of retrieval, but does reflect the relative retrieval number. This is because it is possible to insert records into the buffer after statements have been retrieved from the buffer.

xxxxxxx

The constant AINSERT BUFFER to indicate that the statement resulted from an AINSERT instruction.

vvvvvv

will be null.

**System action:** See the System Action section of the error message(s) which immediately precede this message.

**Programmer response:** Refer to the Programmer Response section of the error messages which immediately precede this message.

**Severity:** 0

---

**ASMA436N Attempt to override invocation parameter in a \*PROCESS statement. Option yyyyyyyy ignored.**

**Explanation:** The option yyyyyyyy specified in a \*PROCESS statement conflicts with an option specified either in the ASMAOPT file or in an invocation parameter.

**System action:** If installation option PESTOP is specified, the assembler stops. If installation option NOPESTOP is specified, the assembly continues using the option specified in the ASMAOPT file or the invocation parameters.

**Programmer response:** Correct the \*PROCESS statement and resubmit the assembly.

**Severity:** 2

---

**ASMA437N Attempt to override invocation parameter in a \*PROCESS statement. Suboption yyyyyyyy of xxxxxxxx option ignored.**

**Explanation:** The suboption yyyyyyyy of option xxxxxxxx specified on a \*PROCESS statement conflicts with a suboption specified in either the ASMAOPT file or in the invocation parameters.

**System action:** If installation option PESTOP is specified, the assembler stops. If installation option NOPESTOP is specified, the assembly continues using the suboption specified in the \*PROCESS OVERRIDE statement.

**Programmer response:** Correct the \*PROCESS statement and resubmit the assembly.

**Severity:** 2

---

**ASMA438N Attempt to override ASMAOPT parameter. Option yyyyyyyy ignored**

**Explanation:** The option yyyyyyyy specified as an invocation parameter overrides the option specified in the ASMAOPT file (CMS or z/OS) or Librarian member (z/VSE).



## Assembly error diagnostic messages

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues using the option specified in the ASMAOPT file (z/OS and CMS) or library member (z/VSE).

**Programmer response:** Remove the option from the invocation parameters and resubmit the assembly.

**Severity:** 2

---

### ASMA439N Attempt to override ASMAOPT parameter. Suboption *yyyyyyyy* of option *xxxxxxx* ignored

**Explanation:** The suboption *xxxxxxx* of options *yyyyyyyy* specified in an invocation parameter overrides the suboption specified in the ASMAOPT file (z/OS and CMS) or library member (z/VSE).

**System action:** If installation option PESTOP is specified, the assembly stops. If installation option NOPESTOP is specified, the assembly continues using the suboption specified in the ASMAOPT file (z/OS and CMS) or library member (z/VSE).

**Programmer response:** Remove the suboption from the invocation parameters and resubmit the assembly.

**Severity:** 2

---

### ASMA440N Attempt to override OVERRIDE parameter in \*PROCESS statement. Option *yyyyyyyy* ignored.

**Explanation:** The option *yyyyyyyy* specified on a \*PROCESS statement conflicts with an option specified in a previous \*PROCESS OVERRIDE statement.

**System action:** If installation option PESTOP is specified, the assembler stops. If installation option NOPESTOP is specified, the assembly continues using the option specified in the \*PROCESS OVERRIDE statement.

**Programmer response:** Correct the \*PROCESS statement and resubmit the assembly.

**Severity:** 2

---

### ASMA441N Attempt to override OVERRIDE parameter in a \*PROCESS statement. Suboption *yyyyyyyy* ignored.

**Explanation:** The suboption *yyyyyyyy* of option *xxxxxxx* specified on a \*PROCESS statement conflicts with a suboption specified in a previous \*PROCESS OVERRIDE statement.

**System action:** If installation option PESTOP is specified, the assembler stops. If installation option NOPESTOP is specified, the assembly continues using the suboption specified in the \*PROCESS OVERRIDE statement.

**Programmer response:** Correct the \*PROCESS statement and resubmit the assembly.

**Severity:** 2

---

### ASMA442N ASMAOPT internal buffer full - some options ignored.

**Explanation:** The length of the options list provided by the ASMAOPT file, including the delimiting commas inserted by the assembler, exceeds 32766 bytes.

**System action:** The record which caused the message to be generated, together with those records following, will be ignored.

**Programmer response:** Reduce the length of the options list provided by the ASMAOPT file.

**Severity:** 2

---

### ASMA443N ASMAOPT record format invalid - options provided via ASMAOPT ignored

**Explanation:** The ASMAOPT DD statement or ASMAOPT FILEDEF refers to a file with a record format that is neither fixed-length nor variable-length.

**System action:** The ASMAOPT file is not processed and any options it contains are ignored.

**Programmer response:** Supply a file which is either fixed-length or variable-length record format.

**Severity:** 2

---

### ASMA500W Requested alignment exceeds section alignment

**Explanation:** The section alignment is lower than that requested on the instruction and hence the actual alignment may not be honored.

**System action:** The requested alignment is ignored.

| **Programmer response:** Change the requested  
| alignment to be less than or equal to that of the section,  
| or ensure that the desired alignment is achieved during  
| program linking and loading.

| **Severity:** 4

---

### ASMA700I *exit-type: exit supplied text*

**Explanation:** The user supplied exit for *exit-type* exit has requested the assembler to issue this message with the *exit supplied text*.

**System action:** None

**Programmer response:** Check the user exit documentation for the cause of this message and for the correct response.

**Severity:** 0

---

**ASMA701W** *exit-type: exit supplied text*

**Explanation:** The user supplied exit for *exit-type* exit has requested the assembler to issue this message with the *exit supplied text*.

**System action:** None

**Programmer response:** Check the user exit documentation for the cause of this message and for the correct response.

**Severity:** 4

---

**ASMA702E** *exit-type: exit supplied text*

**Explanation:** The user supplied exit for *exit-type* exit has requested the assembler to issue this message with the *exit supplied text*.

**System action:** None

**Programmer response:** Check the user exit documentation for the cause of this message and for the correct response.

**Severity:** 8

---

**ASMA703S** *exit-type: exit supplied text*

**Explanation:** The user supplied exit for *exit-type* exit has requested the assembler to issue this message with the *exit supplied text*.

**System action:** None

**Programmer response:** Check the user exit documentation for the cause of this message and for the correct response.

**Severity:** 12

---

**ASMA704C** *exit-type: exit supplied text*

**Explanation:** The user supplied exit for *exit-type* exit has requested the assembler to issue this message with the *exit supplied text*.

**System action:** None

**Programmer response:** Check the installation documentation for the cause of this message and for the correct response.

**Severity:** 16

---

**ASMA710I** *function-name: function-supplied text*

**Explanation:** The user supplied function *function-name* has requested the assembler to issue this message with the *function-supplied text*.

**System action:** None

**Programmer response:** Check the external function documentation for the cause of this message and for the correct response.

**Severity:** 0

---

**ASMA711W** *function-name: function-supplied text*

**Explanation:** The user supplied function *function-name* has requested the assembler to issue this message with the *function-supplied text*.

**System action:** None

**Programmer response:** Check the external function documentation for the cause of this message and for the correct response.

**Severity:** 4

---

**ASMA712E** *function-name : function-supplied text*

**Explanation:** The user supplied function *function-name* has requested the assembler to issue this message with the *function-supplied text*.

**System action:** None

**Programmer response:** Check the external function documentation for the cause of this message and for the correct response.

**Severity:** 8

---

**ASMA713S** *function-name : function-supplied text*

**Explanation:** The user supplied function *function-name* has requested the assembler to issue this message with the *function-supplied text*.

**System action:** None

**Programmer response:** Check the external function documentation for the cause of this message and for the correct response.

**Severity:** 12

---

**ASMA714C** *function-name : function-supplied text*

**Explanation:** The user supplied function *function-name* has requested the assembler to issue this message with the *function-supplied text*.

**System action:** None

**Programmer response:** Check the external function documentation for the cause of this message and for the correct response.

**Severity:** 16

---

### Abnormal assembly termination messages

Whenever an assembly cannot complete, High Level Assembler provides a message and, in some cases, a specially formatted dump for diagnostic information. This might indicate an assembler malfunction or it might indicate a programmer error. The statement causing the error is identified and, if possible, the assembly listing up to the point of the error is printed. The messages in this book give enough information to enable you to correct the error and reassemble your program, or to determine that the error is an assembler malfunction.

#### Note:

If SYSPRINT or SYSLST (z/VSE) is unavailable, the assembler uses the macro WTO with a route code of 11 and a descriptor code of 7, or the system defaults, to output the message(s).

#### Messages

---

##### ASMA930U LOAD OF ASMA93 PHASE FAILED; INSUFFICIENT GETVIS STORAGE OR PHASE NOT FOUND

**Explanation:** The assembler attempted to load the phase ASMA93, but the load failed either because there was insufficient GETVIS storage available to complete the load, or the phase could not be found.

**Note:** This message is only produced in uppercase English.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check the LIBDEF chain to ensure that the sublibrary containing High Level Assembler is correctly concatenated. If it is, you should consider increasing the partition size.

**Severity:** 20

---

##### ASMA932U Unable to load specified EXIT module - xxxxxxx

**Explanation:** The assembler attempted to load the named exit module, but the load failed.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check that the specified exit module is in a library accessible by the assembler.

**Severity:** 20

---

##### ASMA933U UNABLE TO LOAD SPECIFIED MESSAGES MODULE - xxxxxxxx

**Explanation:** The assembler attempted to load the named messages module, but the load failed. The name of the messages module is determined from the value specified in the LANGUAGE option.

**Note:** This message is only produced in uppercase English.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check that you have correctly specified the correct messages module using the LANGUAGE option, and that the specified messages module is in a library accessible by the assembler.

**Severity:** 20

---

##### ASMA934U UNABLE TO LOAD DEFAULT OPTIONS MODULE - xxxxxxxx

**Explanation:** The assembler attempted to load the named default options module, but the load failed.

**Note:** This message is only produced in uppercase English.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check that the default options module is in a library accessible by the assembler.

**Severity:** 20

---

##### ASMA935U One or more required files not available

**Explanation:** The assembler encountered an error when attempting to open a required file.

**System action:** Before this message is issued, one or more associated messages are issued that describe which file or files could not be opened. After this message is issued, the assembly stops.

**Programmer response:** Check the associated message or messages.

**Severity:** 20



---

### ASMA936U Assembly terminated due to errors in invocation parameters

**Explanation:** The assembler detected an error in one or more of the parameters specified when the assembler was invoked, and the installation default value for the PESTOP assembler option is YES.

**System action:** Before this message is issued, one or more associated messages are issued that describe which parameter or parameters were in error. After this message is issued, the assembly stops.

**Programmer response:** Check the associated message or messages. Invoke the assembler with correct invocation parameters. Do not attempt to override the fixed installation defaults.

**Severity:** 20

---

### ASMA937U Unable to load specified translation table - xxxxxxxx

**Explanation:** The assembler attempted to load the translation table called xxxxxxxx, but the load failed. The name of the translation table is determined from the value specified in the TRANSLATE option.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check you have correctly specified the translation table module using the TRANSLATE option, and the module is in a library accessible by the assembler.

**Severity:** 20

---

### ASMA938U Module xxxxxxxx is not a valid translation table

**Explanation:** The translation table specified in the TRANSLATE option is not valid.

**System action:** The assembly stops.

**Programmer response:** Ensure the translation table is generated according to the instructions described in Appendix L, "How to generate a translation table," on page 407.

**Severity:** 20

---

### ASMA939U Unable to load external function module - xxxxxxxx

**Explanation:** The assembler attempted to load the external function module xxxxxxxx, but the load failed.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Check that the specified module is in a library accessible by the assembler, and that the external function name has been spelled correctly in the SETAF or SETCF statement.

**Severity:** 20

---

### ASMA940U *exit-type* exit has requested termination during operation processing; exit error text: < none | error text >

**Explanation:** The user supplied exit for *exit-type* failed when processing an *operation* request. The exit might have provided *error text* to assist in determination of the failure.

**System action:** The assembly stops.

**Programmer response:** Check the specified exit program for the cause of failure.

**Severity:** 20

---

### ASMA941U *external function name* has requested termination during processing.

**Explanation:** The user supplied external function *external function name* failed during processing.

**System action:** The assembly stops.

**Programmer response:** Check the specified external function program for the cause of failure.

**Severity:** 20

---

### ASMA942U xxxxxxxx IS NOT A VALID MODULE

**Explanation:** The default options module ASMADOPT is not in the required format for this release of the assembler. The assembler checks to ensure the release of the module is the same as that of the assembler.

**Note:** This message may be produced in uppercase English, even if you have specified a different language.

**System action:** The assembly terminates

**Programmer response:** Ensure that you have the correct version of the ASMADOPT module available. You might need to reassemble your default options module with the current ASMAOPT macro.

**Severity:** 20

---

### ASMA943U Unable to find listing header *nnn*

**Explanation:** The assembler tried to produce a heading line in the assembler listing but could not find the heading. This can be caused if the assembler load module has been corrupted.

**System action:** The assembly is aborted.

**Programmer response:** Reassemble the program; it might assemble correctly. If it does not reassemble without error, save the output from the assembly, and the input source(s), and contact IBM for support.

**Severity:** 20

## Abnormal assembly termination messages

---

**ASMA944U** LOAD OF ASMA93 MODULE FAILED.  
INSUFFICIENT GETMAIN STORAGE,  
OR MODULE NOT FOUND

**Explanation:** The assembler attempted to load the module ASMA93, but the load failed either because there was insufficient main storage available to complete the load, or the module could not be found, or the Assembler was dynamically invoked by an APF-authorized program yet the Assembler does not reside in an APF-authorized library.

**Note:** This message is only produced in uppercase English.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** on z/OS, ensure that the correct High Level Assembler load library is available in the standard load module search order. If the assembler is invoked by an APF-authorized program then ensure that the assembler resides in an APF-authorized library. Check that there is sufficient virtual storage available to the assembler and consider increasing the region size.

On CMS, ensure that the correct mini disk containing the High Level Assembler modules is being accessed. If it is, consider increasing your virtual machine storage size.

**Severity:** 20

---

**ASMA945U** Unable to load code page xxxxxxxx

**Explanation:** The assembler attempted to load the Code Page module called xxxxxxxx, but the load failed. The name of the module is determined from the value specified in the CODEPAGE option.

**System action:** The assembly stops.

**Programmer response:** Check that you have correctly specified the Code Page module using the CODEPAGE option, and that the module is in a library accessible by the assembler.

**Severity:** 20

---

**ASMA946U** Module ASMAxxxx is not a valid code page module.

**Explanation:** The code page module specified in the CODEPAGE option is not valid.

**System action:** The assembly stops.

**Programmer response:** Ensure the code page module is generated according to the instructions described in Appendix M, "How to generate a Unicode translation table," on page 409.

**Severity:** 20

---

**ASMA950U** End of statement flag was expected in Macro Edited Text, but was not found - MACRO EDITOR is suspect

---

**ASMA951U** The MACRO GENERATOR has encountered untranslatable Macro Edited Text

---

**ASMA952U** Bad SET symbol name field or LCL/GBL operand - check the Macro Edited Text

---

**ASMA953U** Bad subscript on SET symbol - check the Macro Edited Text

---

**ASMA954U** Character expression followed by bad subscripts - check the Macro Edited Text

---

**ASMA955U** A right parenthesis with no matching left parenthesis was found in an expression - check the Macro Edited Text or the expression analysis work area

---

**ASMA956U** Multiple subscripts or bad SET symbol terminator - check the Macro Edited Text

---

**ASMA957U** Bad terminator on created SET symbol - check the Macro Edited Text

---

**ASMA958U** Bad terminator on parameter - check the Macro Edited Text

---

**ASMA960U** A bad internal file number has been passed to the xxxxxxxx internal storage management routine

---

**ASMA961U** An invalid storage request has been made, or the free storage chain pointers have been destroyed

---

**ASMA962U** A zero block address or bad block number has been passed to an internal storage management routine

---

**ASMA963U** Invalid pointer at entry to utility routine

---

**ASMA964U** Macro Edited Text Flag is not ICTL

**Explanation:** The assembly stops because of one of the errors described in ASMA950U through ASMA964U. This usually is caused by an error in the assembler itself. Under certain conditions, however, the assembly can be rerun successfully.

**System action:** The assembly stops and a formatted abnormal termination dump is produced. Depending on where the error occurred, the assembly listing up to the failing statement might also be produced. The dump usually indicates which statement was being processed at the time of abnormal termination. It also might include contents of the assembler registers and work areas and other status information for use by an IBM support representative.

**Programmer response:** Check the statement that was being processed at the time of abnormal termination. Correct any errors in it or, if the statement is long or complex, rewrite it. Reassemble the program; it might assemble correctly. However, even if the program assembles correctly, there might be a problem with the assembler. Save the abnormal termination dump, the assembly listing (if one was produced), and the source program, and contact IBM for support.

**Severity:** 20

---

**ASMA966U Insufficient partition GETVIS storage to load xxxxxxxx; increase the partition GETVIS size**

**Explanation:** The assembler attempted to load the named phase, but there was not enough GETVIS storage available for the phase.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Increase the amount of GETVIS storage allocated to the partition.

**Severity:** 20

---

**ASMA967U Insufficient partition GETVIS storage for assembly initialization; increase the partition GETVIS size**

**Explanation:** The assembler attempted to acquire an initial block of storage, but there is not enough GETVIS storage available.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Increase the amount of GETVIS storage allocated to the partition.

**Severity:** 20

---

**ASMA970U Statement complexity exceeded, break the statement into segments, and rerun the assembly**

**Explanation:** The statement is too complex to be evaluated by the macro generator phase of the assembler. It overflowed the evaluation work area of the assembler. Normally, there is no assembler malfunction; the statement can be corrected and the program reassembled successfully.

**System action:** A special abnormal termination dump (High Level Assembler interrupt and diagnostic dump) follows the message. The statement causing termination is SETA, SETB, SETC, AGO, or AIF. The dump does not indicate which statement caused termination; however, it might show the last statement generated in the macro. The dump might also include contents of the assembler registers and work areas and other status information for use by IBM or your assembler maintenance programmers in determining the cause of the termination. However, it is not needed unless the error persists. This information could be helpful in diagnosing and fixing an assembler error.

**Programmer response:** Check the statement that caused termination. Rewrite the statement or split it into two or more statements. Reassemble the program; it should assemble correctly. However, if the error persists, there might be an assembler malfunction. Save the abnormal termination dump, the assembly listing (if one was produced), and the input source(s), and contact IBM for support.

**Severity:** 20

---

**ASMA971U Insufficient storage available for Macro Editor work area**

---

**ASMA972U Virtual storage exhausted; increase the SIZE option**

**Explanation:** The size of the dynamic storage area allocated for assembler buffer areas, tables, and work areas, as specified in the SIZE option, is not enough for the assembly to complete.

**System action:** A special abnormal termination dump (High Level Assembler interrupt and diagnostic dump) follows the message. The dump usually indicates the statement being processed when the assembler determined there was not enough dynamic storage available to continue. Depending on where the error occurred, the assembly listing up to the statement being processed might also be produced. The other information in the dump, such as register and work area contents, is not needed.

**Programmer response:** Increase the value specified in the SIZE option, or split the assembly into two or more assemblies. Check for conditional assembly language loops in open code that could cause the symbol table to overflow.

**Severity:** 20

---

**ASMA974U Insufficient storage available to satisfy the SIZE option**

**Explanation:** The assembler attempted to acquire the amount of storage specified in the SIZE option, but there was not enough available storage in the region (z/OS), virtual machine (CMS), or partition GETVIS (z/VSE).

## Abnormal assembly termination messages

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Increase the region size (z/OS), the virtual machine size (CMS), or the partition GETVIS (z/VSE) size, or reduce the size requested in the SIZE option.

**Severity:** 20

---

### ASMA975U SIZE option specifies insufficient storage for assembly

**Explanation:** The SIZE option was specified as MAX-*nnn*K or MAX-*nn*M, but the amount of storage available to the assembler using this formula is not enough for the assembly to continue. The assembler requires a minimum of either 200K bytes or 10 times the work file blocksize, plus 20K, of working storage in the region (z/OS), virtual machine (CMS), or partition GETVIS (z/VSE) to proceed.

**System action:** The assembly stops and no listing is produced.

**Programmer response:** Increase the region size (z/OS), virtual machine size (CMS), or the partition GETVIS (z/VSE) size, or reduce the amount of storage to be reserved in the MAX-*nnn*K or MAX-*nn*M form of the SIZE option.

**Severity:** 20

---

### ASMA976U Statement too complex for expression analysis

**Explanation:** The statement is too complex to be analyzed by the expression analysis routine of the assembler. It overflowed the analysis work area. The size of the analysis work area is the same as the work file block size. Normally, there is no problem with the assembler. The statement can be rewritten to simplify it, and the program reassembled successfully.

**System action:** The assembly stops and a formatted abnormal termination dump is produced. The dump indicates which statement was being processed at the time of abnormal termination. It also includes the contents of the assembler registers and work areas and other status information that might be required by an IBM support representative if the problem persists.

**Programmer response:** Check the statement that was being processed at the time of abnormal termination. Rewrite the statement or split it into two or more statements. Alternatively, increase the work file block size. Reassemble the program; it should assemble correctly. However, if the problem persists, there might be a problem with the assembler. Save the abnormal termination dump, the assembly listing (if one was produced), and the input source(s), and contact IBM for support.

**Severity:** 20

---

### ASMA990U Location Counter does not match symbol table value

**Explanation:** A difference has been detected between the symbol table and the location counter. The assembly stops and a special abnormal termination dump (High Level Assembler interrupt and diagnostic dump) is taken. The listing is not completed.

**System action:** The High Level Assembler interrupt and diagnostic dump shows the statement that was being printed when the difference between the location counter and the symbol table was detected.

**Programmer response:** Reassemble the program using NOALIGN. If alignment is needed, use CNOP or DS to force alignment.

**Severity:** 20

---

### ASMA998U The assembler could not resume reading a LIBRARY member because it could not FIND the member again

**Explanation:** The assembly stops, because the assembler cannot find a COPY member that it has already read. This usually is caused by an error in the assembler itself or by an Operating System I/O error. Under certain conditions, however, the assembly can be rerun successfully.

**System action:** A special abnormal termination dump (High Level Assembler interrupt and diagnostic dump) follows the message. The dump usually indicates which statement caused termination. It also might include contents of the assembler registers and work areas and other status information for use by IBM or your assembler maintenance programmers in determining the cause of the termination.

**Programmer response:** Reassemble the program; it might assemble correctly. If it does not reassemble without error, save the abnormal termination dump, the assembly listing (if one was produced), and the input source(s), and contact IBM for support.

**Severity:** 20

---

### ASMA999U Assembly terminated - SYNAD Exit taken - Permanent I/O error on xxxxxx data set

**Explanation:** The assembly was stopped because of a permanent I/O error on the data set indicated in the message. This is usually caused by a machine or an operating system error. The assembly usually can be rerun successfully. This message also appears on the console output device.

**System action:** A special abnormal termination dump (High Level Assembler interrupt and diagnostic dump) follows the message. Depending on where the error occurred, the assembly listing up to the bad statement might also be produced. The dump usually indicates



which statement caused termination. It also might include contents of the assembler registers and work areas and other status information for use by IBM or your assembler maintenance programmers in determining the cause of the termination.

**Programmer response:** If the I/O error is on SYSIN or SYSLIB, you might have concatenated the input or library data sets incorrectly. Make sure that all input or library data sets have the same device class (all DASD or all tape). Please also check that file attributes such as DSORG, RECFM, LRECL, and BLKSIZE have been correctly specified.

If the I/O error is on SYSUT1, check that SYSUT1 is allocated to a single volume—the assembler does not support a multivolume work file.

Reassemble the program; it might assemble correctly. If it does not reassemble without error, save the abnormal termination dump, the assembly listing (if one was produced), and the input source(s), and contact IBM for support. Also, if the program assembles correctly, submit a copy of the listing and input source(s) of the correct assembly.

**Severity:** 20

---

## ASMAHL Command Error Messages (CMS)

---

### ASMACMS002E File *fn ft fm* not found

**Explanation:** The file name you included in the ASMAHL command does not correspond to the names of any of the files on your disks.

**Supplemental Information:** The variable file name, file type, and file mode in the text of the message indicate the file that could not be found.

**System action:** RC=28. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Reissue the ASMAHL with the correct file name.

---

### ASMACMS003E Invalid option *option*

**Explanation:** You have included an option that is not correct with your ASMAHL command.

**Supplemental Information:** The variable option in the text of the message indicates the option that is not correct.

**System action:** RC=24. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Check the format of the ASMAHL command, and reissue the command with the correct option.

---

### ASMACMS004E Improperly formed option *option*

**Explanation:** You have included an improperly formed option with your ASMAHL command.

**Supplemental Information:** The variable option in the text of the message indicates the improperly formed option.

**System action:** RC=24. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Check the format of the ASMAHL command, and reissue the command with the correct option.

---

### ASMACMS005E Truncation of options may have occurred because of tokenized PLIST format

**Explanation:** The options have been passed to the ASMAHL command in tokenized PLIST format. Any options passed might have been truncated to 8 characters. This message is only issued when an error has been detected in one of the options that was specified.

**System action:** The options are accepted as entered but might have been truncated.

**Programmer response:** If the options have been truncated, invoke the ASMAHL command with the extended parameter list. If the SYSPARM option has been truncated, specify SYSPARM(?).

---

### ASMACMS006E No read/write disk accessed

**Explanation:** Your virtual machine configuration does not include a read/write disk for this terminal session, or you failed to specify a read/write disk.

**System action:** RC=36. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Issue an ACCESS command specifying a read/write disk.

---

### ASMACMS007E File '*fn ft fm*' does not contain fixed length 80 character records

**Explanation:** The source file you specified in the ASMAHL command does not contain fixed-length records of 80 characters.

**Supplemental Information:** The variable file name, file type, and file mode in the text of the message indicate the file that is in error.

**System action:** RC=32. The command cannot be processed.

**Programmer response:** You must reformat your file into the correct record length. CMS XEDIT or COPYFILE can be used to reformat the file.

## ASMAHL Command Error Messages (CMS)

---

### ASMACMS010E file name omitted and FILEDEF 'ddname' is undefined

**Explanation:** You have not included a file name in the ASMAHL command, and no FILEDEF could be found for the *ddname* specified.

**System action:** RC=24. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Reissue the ASMAHL command and specify a file name, or issue a FILEDEF for the *ddname* specified.

---

### ASMACMS011E file name omitted and FILEDEF 'ddname' is not for DISK

**Explanation:** You have not included a file name in the ASMAHL command, and the FILEDEF for the *ddname* specified is not for DISK.

**System action:** RC=24. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Reissue the ASMAHL command and specify a file name, or reissue the FILEDEF for the *ddname* specified with a device type of 'DISK'.

---

### ASMACMS038E Filename conflict for the SYSIN FILEDEF.

**Explanation:** The file name specified on the ASMAHL command conflicts with the file name on the FILEDEF for the SYSIN *ddname*.

**System action:** RC=40. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Reissue the FILEDEF command or the ASMAHL command specifying the same file name.

---

### ASMACMS040E Saved segment xxxxxxxx does not exist

**Explanation:** The specified saved segment has not been included in the System Names Table (SNT).

**System action:** RC=40. Processing of the command terminates.

**Programmer response:** See your system administrator.

---

### ASMACMS041E The storage for saved segment xxxxxxx is already in use

**Explanation:** The storage for the specified saved segment has already been used by another saved segment.

**System action:** RC=40. Processing of the command terminates.

**Programmer response:** See your system administrator.

---

### ASMACMS042E SEGMENT error nnn loading saved segment xxxxxxxx

**Explanation:** An error occurred when the ASMAHL command attempted to load the specified saved segment.

**System action:** RC=40. Processing of the command terminates.

**Programmer response:** See your system administrator.

---

### ASMACMS043E DIAGNOSE error nnn loading saved segment xxxxxxxx

**Explanation:** An error occurred when the ASMAHL command attempted to load the specified saved segment.

**System action:** RC=40. Processing of the command terminates.

**Programmer response:** See your system administrator.

---

### ASMACMS044E NUCXLOAD error nnn loading xxxxxxx module

**Explanation:** An error occurred when the ASMAHL command attempted to load the specified module.

**System action:** RC=40. Processing of the command terminates.

**Programmer response:** See your system administrator.

---

### ASMACMS052E Option list exceeds 512 characters.

**Explanation:** The string of options that you specified with your ASMAHL command exceeded 512 characters in length.

**System action:** RC=24. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Reissue your ASMAHL command with fewer options specified.

---

### ASMACMS062E Invalid character c in file name xxxxxxx

**Explanation:** A character that is not permitted was specified in the file name specified on the ASMAHL command.

**System action:** RC=40. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Check the format of the option

with its correct parameters, and reissue the command with the correct parameter.

---

### ASMACMS070E Left parenthesis '(' required before option list

**Explanation:** An option was specified after the file name but before the left parenthesis on the ASMAHL command.

**System action:** RC=40. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Issue the ASMAHL command again with the option specified after the left parenthesis. Only the file name can be specified before the left parenthesis.

---

### ASMACMS074E Required module xxxxxxxx MODULE not found

**Explanation:** The ASMAHL command was unable to load the specified module.

**System action:** RC=40. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Verify you have accessed the disk containing the assembler and issue the ASMAHL command again.

---

### ASMACMS075E Device device invalid for xxxxxxxx

**Explanation:** The device specified in your FILEDEF command cannot be used for the input or output operation that is requested in your program. For example, you have tried to read data from the printer or write data to the reader.

**Supplemental Information:** The variable device name in the text of the message indicates the incorrect device that was specified.

**System action:** RC=40. Processing of the command terminates. The system remains in the same status as before the command was entered.

**Programmer response:** Reissue your FILEDEF command, specifying the correct device for the required input operation.

---

### ASMACMS076E xxxxxxxx MODULE IS NOT IN RELEASE 6 FORMAT

**Explanation:** The module xxxxxxxx is not in the required format for Release 6.

**Note:** This message is only produced in uppercase English.

**System action:** RC=40. Processing of the command terminates.

**Programmer response:** Ensure that you have the correct version of the module available. Check the disks you have linked, and make sure you are not accessing modules from an earlier release of High Level Assembler. If the module is ASMADOPT, you might need to reassemble your default options module with the ASMAOPT macro provided with High Level Assembler Release 6. If you cannot resolve the problem, contact your High Level Assembler maintenance programmer, or your IBM service representative.

## ASMAHL Command Error Messages (CMS)



---

## Appendix H. User interface macros

The macros identified in this appendix are provided as programming interfaces by High Level Assembler.

**Attention:** Do not use any High Level Assembler macros, other than those identified in this appendix, as programming interfaces.

The following macros intended for customers are all General-Use Programming Interfaces.

- ASMADATA** Maps the records in the associated data file.
- ASMAEFNP** Maps the parameter list passed to external function routines for the SETAF and SETCF conditional assembler instructions.
- ASMAXFMB** On z/OS and CMS, generates the Filter Management Table used by the sample ADATA user exit ASMAXADT.
- ASMAXITP** Maps the parameter list passed to the assembler user exits.



---

## Appendix I. Sample ADATA user exits (z/OS and CMS)

ASMAXADT, ASMAXADC, and ASMAXADR are sample ADATA exits supplied with High Level Assembler.

---

### Sample ASMAXADT user exit to filter records

This sample ADATA exit handles the details of interfaces to the assembler, and provides associated data (ADATA) records to any of a number of *filter modules* that inspect the records to extract the information they require. This allows filter modules to be added or modified without impacting either the exit or the other filter modules.

The design of the exit:

- Supports multiple simultaneous filter modules.
- Simplifies the ADATA record interface for each filter, because you don't need to know about the complex details of interacting directly with the assembler.
- Supports filter modules written in high level languages.

The three components that make up the functional ADATA exit are:

1. The exit routine, ASMAXADT, which is invoked by High Level Assembler
2. A table of filter module names, contained in a *Filter Management Table* (FMT) module ASMAXFMT. The FMT is loaded by the exit routine.
3. The filter modules. These are loaded by the exit as directed by the FMT. A sample filter module, ASMAXFLU, is provided with High Level Assembler.

### Preparing the exit

Before the exit can be used it must be assembled and link-edited, and the load module placed in a library in the standard search order. ASMAXADT, as supplied, has the following attributes: reusable, reenterable, amode(24), rmode(24).

Refer to Chapter 4, "Providing user exits," on page 87 for further information about coding and preparing user exits.

**Preparing the Filter Management Table:** The names of the filter modules to be invoked by the user exit are contained in the Filter Management Table (FMT). The FMT is generated by using the macro ASMAXFMB. The names of the filter modules are specified as operands to the ASMAXFMB macro. Figure 63 shows an example of how to create an FMT that causes the filters MYFILT, YOURFILT, HERFILT, HISFILT, and OURFILT to be invoked by the exit.

---

```
ASMAXFMT Title 'ADATA Exit Filter Management Table'  
          ASMAXFMB MYFILT,YOURFILT,HERFILT,HISFILT,OURFILT  
          END
```

---

*Figure 63. Creating a filter management table*

The object file produced from the assembly must be link-edited, and the load module placed in a library in the standard search order. ASMAXFMT, as supplied, has the following attributes: reusable, non-reenterable, non-shareable.

## Sample ASMAXADT user exit to filter records

You can specify an initial character string as part of the filter operand that is passed to the filter routine during initialization. Figure 64 shows two filter routines: MYFILT, that receives the characters “A,B,C”, and ASMAXFLU, that receives the characters “DUMP”.

---

```
ASMAXFMT Title 'ADATA Exit Filter Management Table'
        ASMAXFMB (MYFILT,'A,B,C'),(ASMAXFLU,'DUMP')
        END
```

---

*Figure 64. Passing initial character string to filter routines*

The default FMT control section (CSECT) name is ASMAXFMT. You can specify a different CSECT name using the SECT keyword on the ASMAXFMB macro. Figure 65 shows how to generate a CSECT name of MYFMT.

---

```
ASMAXFMT Title 'ADATA Exit Filter Management Table'
        ASMAXFMB SECT=MYFMT,(MYFILT,'A,B,C'),YOURFILT
        END
```

---

*Figure 65. Generating an alternative CSECT name*

## Preparing the filter modules

The exit routine loads the Filter Management Table (FMT) module. The filter modules specified in the FMT are then loaded by the exit routine. Each filter module is called by the exit in three ways: once to process an OPEN request, multiple times to process ADATA records, and once to process a CLOSE request.

### Call interface

The filter modules must be placed in a library in the standard search order.

Each filter is called by the exit using the standard call interface in the following form:

```
CALL filter(exit_type,action,return_code,handle,record_length,record)
```

The exit branches to the filter module using the BASR assembler instruction.

### Registers on entry

Standard OS linkage conventions are used, and the registers on entry to the filter module are:

- R13 contains the address of a standard 18-word save area
- R14 contains the return address to the exit
- R15 contains the filter's entry point address
- R1 contains the address of a list of six fullwords that address:
  1. A fullword containing the exit\_type
  2. A fullword integer containing the action code
  3. A fullword integer where the filter puts the return\_code
  4. A 4-fullword handle area
  5. A fullword integer containing the ADATA record\_length
  6. The ADATA record

The high-order bit of the last fullword address is set to one.

Figure 66 on page 393 shows the six fullwords in the parameter list.




Figure 66. Filter module parameter list format

### Parameters on entry

The six parameters are:

- exit\_type** (Input) The address of a fullword of storage that indicates the exit type. The value is always 4, to indicate an ADATA exit.
- action** (Input) The address of a fullword integer that can be one of the following three values:
- 0** OPEN Request. Open and initialize the filter. No ADATA record is available with this call, although there may be initial character string data supplied.  
The exit accepts the following return codes:
    - 0** The open action was successful. The exit subsequently calls the filter module to inspect and process each ADATA record.
    - 12** The open action was unsuccessful. The filter module is assumed to have closed itself, and is not called again.
  - 1** CLOSE Request. The exit is requesting the filter module to close itself. No ADATA record is available with this call and no further calls are made to the filter module.  
The exit accepts the following return codes:
    - 0** The filter module has closed successfully. The exit can delete the filter.
    - 12** The filter module is assumed to have closed itself, and is not called again. The exit can delete the filter.
  - 3** PROCESS Request. A record is available to the filter module for processing. The ADATA record should not be modified.

## Sample ASMAXADT user exit to filter records

The exit accepts the following return codes:

- 0        The filter module has completed its processing of this record, and is ready to accept further records.
- 12       The filter module is assumed to have closed itself, and is not called again.

<b>return_code</b>	(Output) The address of a fullword integer where the filter module should place a return code. Valid return codes are described under each action.
<b>handle</b>	(Input/Output) The address of a 4-fullword area of storage that is initialized to zero before the OPEN (action=0) call to the filter. Its contents are preserved across subsequent calls. The handle can be used in any way by the filter module; for example, to address working storage for a reenterable filter module.
<b>record_length</b>	(Input) The address of a fullword integer containing the length of the ADATA record. A length is provided for PROCESS (action=3) calls, and for OPEN (action=0) calls when you supply an initial character string.
<b>record</b>	(Input) The address of the ADATA record. This points to the ADATA record for PROCESS (action=3) calls, and to the initial character string for OPEN (action=0) calls.

### Information messages

If all the filter modules request termination before the last ADATA record is processed, the following message is issued and the assembly continues:

- ASMA700I All SYSADATA filter modules requested early termination

### Error diagnostic messages

When the Filter Management Table routine detects an error it directs the assembler to issue message ASMA940U and the assembly stops. The following text might be included in the ASMA940U message:

- SYSADATA exit not coded at same level of interface definition (2) as assembler  
The exit uses version 2 of the exit definition, but the assembler uses a different version.
- SYSADATA exit called for other than SYSADATA  
The exit was invoked with a valid type, but the type is not one that the exit can process. This is probably caused by an incorrect ADEXIT() suboption of the EXIT assembler option.
- SYSADATA exit not initialized, and not entered for OPEN  
The exit has not yet been initialized, but was not entered with an OPEN request (action=0). There may be a failure in communication between the assembler and the exit.
- SYSADATA exit initialized, but was entered for OPEN  
The exit has been initialized, but was unexpectedly entered with an OPEN request (action=0). There may be a failure in communication between the assembler and the exit.
- SYSADATA exit - Invalid action or operation type requested  
An action was requested that is inconsistent with the type of action the exit is able or was expecting to take. There may be a failure in communication between the assembler and the exit.

- SYSADATA exit expecting input record, zero buffer length found  
The exit was expecting an input record, but the record length was zero. There may be a failure in communication between the assembler and the exit.
- Unable to load xxxxxxxx module. SYSADATA exit failed  
The assembler was unable to load the Filter Management Table module xxxxxxxx. No SYSADATA processing is possible.
- All SYSADATA filter modules failed to open  
All of the filter modules loaded by the exit failed to open. No SYSADATA processing is possible.

## Preparing the sample filter module ASMAXFLU

You can use the supplied filter routine, ASMAXFLU, to:

- Write the names of the primary input and library data sets to a data set.
- Dump the first 32 bytes of each ADATA record to a data set. This function is only performed if you specify DUMP as the initial character string, as shown in Figure 67.

---

```
ASMAXFMT Title 'ADATA Exit Filter Management Table'
          ASMAXFMB (ASMAXFLU,'DUMP')
          END
```

---

Figure 67. Initial character string for ASMAXFLU

## Output from ASMAXFLU

The output from ASMAXFLU is written to a data set defined by the ddname XFLUOUT. The data set record length is 80 bytes. The first record in the data set is a header record, and the last record in the data set is a trailer record. The dump, header, and trailer records are prefixed with an asterisk.

The data set records have one of these formats:

- | Columns | Contents                                       |
|---------|--|
| 1       | Record type: "P"=Primary Input, "L"=Library    |
| 2       | Space  |
| 3–10    | Date, in YYYYMMDD format (spaces for type "L") |
| 11–14   | Time, in HHMM format (spaces for type "L")     |
| 15–58   | Data set name                                  |
| 59–66   | Member name                                    |
| 67–72   | Volume ID where file was found                 |
| 73–80   | Sequencing information                         |

- | Columns | Contents                                |
|---------|---|
| 1       | Record type: "M"=Inline MACRO           |
| 2       | Space                                   |
| 3–15    | "PRIMARY INPUT"                         |
| 16–17   | Space                                   |
| 18–80   | Macro name (can be up to 63 characters) |

## Sample ASMAXADT user exit to filter records

Figure 68 shows a sample data set containing records written by ASMAXFLU:

---

```
-----1-----2-----3-----4-----5-----6-----7-----8

* ASMAXFLU Filter Header Record
*Dump 10000203 00000000 00000008 00000000 00000000 00000000 00000000 00000000
*Dump 10000103 00000000 0000000A B0CC4378 E50BF900 00250000 00000000 00000000
*Dump 10000003 00000000 00000077 F1F9F9F8 F0F7F2F4 F1F9F3F3 F5F6F9F6 60F2F3F4
P 199807241933AINSET3 ASSEMBLE A1 ADISK 00000001
*Dump 10001003 00000000 00000068 A0CF0049 84BC0601 0F008000 40404040 40404040
*Dump 10002003 00000000 00000028 00000000 00000001 00000000 00000000 00000000
*Dump 10003003 00000000 0000009C 00000001 00000000 00000001 00000000 00010000
*Dump 10003003 00000000 0000009C 00000002 00000000 00000002 00000000 00010000
*Dump 10003003 00000000 0000009C 00000003 00000000 00000003 00000000 00010000
*Dump 10003003 00000000 0000009C 00000004 00000000 00000004 00000000 00010000
*Dump 10003003 00000000 0000009C 00000005 00000000 00000005 00000000 00010000
*Dump 10003003 00000000 0000009C 00000006 00000000 00000006 00000000 00010000
*Dump 10004203 00000000 0000002A 00000001 0000000F 01D10000 00010001 00000000
*Dump 10004403 00000000 0000001D 00080000 000F0001 40000000 00000000 C1C9D5E3
*Dump 10006003 00000000 0000003B 0002000D 0000FFFF 00060000 0000D7D9 C9D4C1D9
M PRIMARY INPUT AINSET_TEST_MACRO
M PRIMARY INPUT MAC1
*Dump 10006003 00000000 00000039 00020014 00050001 00060000 0000E3C5 E2E34040
L TEST MACLIB A1 XIT1 ADISK
L TEST MACLIB A1 XIT3 ADISK
*Dump 10006003 00000000 00000033 00010014 00050002 00060000 0000C4E2 C5C3E340
L DSECT MACLIB A1 XIT2 ADISK
*Dump 10006203 00000000 000000A6 00000000 00000003 D7400000 00000000 0000C1C9
*Dump 10006203 00000000 000000A6 00000000 0000001C D7400000 00000000 0000D4C1
*Dump 10006203 00000000 000000A6 00000002 00000000 D3400000 00000000 0000E7C9
*Dump 10006203 00000000 000000A6 00000003 00000000 D3400000 00000000 0000E7C9
*Dump 10006203 00000000 000000A6 00000002 00000000 D3400000 00000000 0000E7C9
*Dump 10009003 00000000 000000B0 00000DF3 000000C8 00000012 00000000 00000000
*Dump 10000203 00000000 00000008 00010000 0000003D 00000000 00000000 00000000
* ASMAXFLU Filter Trailer Record
```

---

Figure 68. Sample output data set from ASMAXFLU

### Error messages

When ASMAXFLU detects an error, it writes an error message to the XFLUOUT data set. The following messages might be written:

- ASMAXFLU called with unknown ADATA Definition Level.  
Check the value of ADATA\_LEVEL in the ADATA record header.
- ASMAXFLU called for other than Assembler ADATA?  
Check the value of ADATA\_VERSION in the ADATA record header.
- ASMAXFLU library record has no member names?  
Check the value of ADMXREF\_MACROS\_NUM in the X'0060' ADATA record.
- ASMAXFLU library record missing member data?  
Check the value of ADMXREF\_MACRO\_NAME\_LEN in the X'0060' ADATA record.
- ASMAXFLU Job-ID record has no file names?  
Check the value of ADJID\_FILES\_NUM in the X'0000' ADATA record.
- ASMAXFLU called with unrecognized action code.  
The action code is not 0, 1, or 3.
- ASMAXFLU called with unrecognized exit type.



The `exit_type` is not 4.

### Assembling and link-editing ASMAXFLU

You must assemble and link-edit ASMAXFLU, placing the load module in a library in the standard search order. ASMAXFLU, as supplied, has the following attributes: non-reusable, non-reenterable, `amode(24)`, `rmode(24)`. See page 392 for details about preparing filter modules.

### Invoking the exit

To invoke the exit, specify the EXIT assembler option as follows:

```
EXIT(ADEXIT(ASMAXADT))
```

If you don't want to use the default filter management table ASMAXFMT, you can specify a different name as follows:

```
EXIT(ADEXIT(ASMAXADT(fmt_name)))
```

where *fmt\_name* is the load module name of the filter management table. See Figure 65 on page 392, which shows you how to generate an alternative filter management table.

---

## Sample ASMAXADC user exit to control record output

This sample ADATA exit uses parameters specified on the assembler EXIT option to determine if it, or the assembler, is to perform output processing for the associated data records, and which record types are to be kept or discarded. The exit will accept records from the assembler, via either a PROCESS request or a WRITE request, and it will decide whether the record should be discarded, output, or perhaps modified and then output. The exit will then decide if an additional record should be inserted, and if so it will build the new record.

For a PROCESS request the exit will set the appropriate flags and return to allow the assembler to perform the output processing. For a WRITE request the exit will perform the output processing itself.

### Preparing the exit

Before the exit can be used it must be assembled and link-edited, and the load module placed in a library in the standard search order. ASMAXADC, as supplied, has the following attributes: reusable, reenterable, `amode(31)`, `rmode(any)`.

Refer to Chapter 4, "Providing user exits," on page 87 for further information about coding and preparing user exits.


### Invoking the exit

To invoke the exit, specify the EXIT assembler option as follows:

```
EXIT(ADEXIT(ASMAXADC(parameter-string)))
```

where *parameter-string* controls what action the exit performs.

## Sample ASMAXADC user exit to control record output



### Default

NOWRITE,TYPE(0:FFFF)

### Abbreviations

W, NOW, T, N

The abbreviations shown here are the minimum number of characters allowed. You can, for example, specify TYP or NOTY.

### WRITE(filename)

Specifies that the exit will perform output processing for the associated data records, instead of the assembler, and optionally use the alternative filename *filename* instead of the default SYSADATA file (z/OS and CMS) or SYSADAT file (z/VSE).

### NOWRITE

Specifies that the assembler will perform output processing for the associated data records as per normal processing.

### TYPE(aaaa:zzzz)

Specifies that these associated data record types will be output as per normal processing. Record types are specified as one to four character hex values, in the form of a list of single record types *aaaa*, or record type ranges *aaaa:zzzz*

### NOTYPE(aaaa:zzzz)

Specifies that these associated data record types will be discarded. Record types are specified the same as for TYPE.

**Note:** The *parameter-string* is processed left to right, so where a conflict occurs for a particular record type the last occurrence will take precedence.

The default processing is to allow all associated data record types to be output by the assembler, as per normal processing. This means, for example, that a *parameter-string* of NOWRITE,TYPE(0:0TYPE(0030) will have the same result as NOTYPE(0030) alone.

## Messages

When the exit detects an error it directs the assembler to issue message ASMA940U and the assembly stops. The following text might be included in the ASMA940U message:

## Sample ASMAXADC user exit to control record output

- SYSADATA exit not coded at same level of interface definition (3) as Assembler  
The exit uses version 3 of the exit definition, but the assembler uses a different version.
- SYSADATA exit called for other than SYSADATA  
The exit was invoked with a valid type, but the type is not one that the exit can process. This is probably caused by an incorrect ADEXIT() suboption of the EXIT assembler option.
- SYSADATA exit not initialized, and not entered for OPEN  
The exit has not yet been initialized, but was not entered with an OPEN request (action=0). There may be a failure in communication between the assembler and the exit.
- SYSADATA exit initialized, but was entered for OPEN  
The exit has been initialized, but was unexpectedly entered with an OPEN request (action=0). There may be a failure in communication between the assembler and the exit.
- SYSADATA exit - Invalid action or operation type requested  
An action was requested that is inconsistent with the type of action the exit is able or was expecting to take. There may be a failure in communication between the assembler and the exit.
- SYSADATA exit - Supplied parameters contain a syntax error  
While parsing the supplied parameter string the exit has detected a syntax error. This is probably caused by an incorrect specification of parameters on the ADEXIT(ASMAXADC(*parameter-string*)) suboption of the EXIT assembler option.
- SYSADATA exit expecting input record, zero buffer length found  
The exit was expecting an input record, but the record length was zero. There may be a failure in communication between the assembler and the exit.

---

## Sample ASMAXADR user exit to reformat records

This sample ADATA exit uses parameters specified on the assembler EXIT option, to determine which associated data record types are to be reformatted from the High Level Assembler Release 5 format back to the Release 4 format. The exit will accept records from the assembler, via a PROCESS request, and it will decide whether the record should be reformatted.

High Level Assembler Release 5 has restructured the associated data records; so this sample exit is provided as a migration aid to allow existing associated data processing utilities to continue to function during the transition from Release 4 to Release 5.

### Preparing the exit

Before the exit can be used it must be assembled and link-edited, and the load module placed in a library in the standard search order. ASMAXADR, as supplied, has the following attributes: reusable, reenterable, amode(31), rmode(any).


Refer to Chapter 4, "Providing user exits," on page 87 for further information about coding and preparing user exits.

### Invoking the exit

To invoke the exit, specify the EXIT assembler option as follows:

```
EXIT(ADEXIT(ASMAXADR(parameter-string)))
```

where *parameter-string* controls what action the exit performs.



#### Default

`REFORMAT(0:FFFF)`

#### Abbreviations

R, N The abbreviations shown here are the minimum number of characters allowed. You can, for example, specify REF or NORE.

#### `REFORMAT(aaaa:zzzz)`

Specifies that these associated data record types will be reformatted from the High Level Assembler Release 5 format back to the Release 4 format. Record types are specified as one to four character hex values, in the form of a list of single record types *aaaa*, or record type ranges *aaaa:zzzz*

#### `NOREFORMAT(aaaa:zzzz)`

Specifies that these associated data record types will not be altered. They will remain in the High Level Assembler Release 5 format. Record types are specified the same as for REFORMAT.

**Note:** The *parameter-string* is processed left to right, so where a conflict occurs for a particular record type the last occurrence will take precedence.

The default processing is to allow all associated data record types to be reformatted. This means, for example, that a *parameter-string* of `REFORMAT(0:FFFF),NOFORMAT(0030)` will have the same result as `NOFORMAT(0030)` alone.

### Messages

When the exit detects an error it directs the assembler to issue message ASMA940U and the assembly stops. The following text might be included in the ASMA940U message:

- SYSADATA exit not coded at same level of interface definition (3) as Assembler

The exit uses version 3 of the exit definition, but the assembler uses a different version.

- SYSADATA exit called for other than SYSADATA

The exit was invoked with a valid type, but the type is not one that the exit can process. This is probably caused by an incorrect ADEXIT() suboption of the EXIT assembler option.

## Sample ASMAXADR user exit to reformat records

- SYSADATA exit not initialized, and not entered for OPEN  
The exit has not yet been initialized, but was not entered with an OPEN request (action=0). There may be a failure in communication between the assembler and the exit.
- SYSADATA exit initialized, but was entered for OPEN  
The exit has been initialized, but was unexpectedly entered with an OPEN request (action=0). There may be a failure in communication between the assembler and the exit.
- SYSADATA exit - Invalid action or operation type requested  
An action was requested that is inconsistent with the type of action the exit is able or was expecting to take. There may be a failure in communication between the assembler and the exit.
- SYSADATA exit - Supplied parameters contain a syntax error  
While parsing the supplied parameter string the exit has detected a syntax error. This is probably caused by an incorrect specification of parameters on the ADEXIT(ASMAXADR(*parameter-string*)) suboption of the EXIT assembler option.
- SYSADATA exit expecting input record, zero buffer length found  
The exit was expecting an input record, but the record length was zero. There may be a failure in communication between the assembler and the exit.

## Sample ASMAXADR user exit to reformat records

---

## Appendix J. Sample LISTING user exit (z/OS and CMS)

ASMAXPRT is a sample LISTING exit supplied with High Level Assembler.

---

### Function

The sample LISTING exit suppresses printing of the High Level Assembler Options Summary, or the Diagnostic Cross Reference and Assembler Summary, or both. It can also print the Options Summary page at the end of the listing, instead of its normal position at the beginning of the listing.

---

### Preparing the exit

Before the exit can be used it must be assembled and link-edited, and the load module (phase) placed in a library in the standard search order. ASMAXPRT, as supplied, has the following attributes: reusable, reenterable, amode(31), rmode(any).

Refer to Chapter 4, “Providing user exits,” on page 87 for further information about coding and preparing user exits.


---

### Invoking the exit

To invoke the exit, specify the EXIT assembler option as follows:

```
EXIT(PRTEXIT(ASMAXPRT(parameter-string)))
```

where *parameter-string* controls what action the exit performs.



#### Default

None. At least one keyword is required.

#### Abbreviations

NOOP, NOSUM

The abbreviations shown here are the minimum number of characters allowed. You can, for example, specify NOOPTI or NOSUMM.

#### NOOPTION

Suppress the Options Summary

#### NOSUMMARY

Suppress the Diagnostic Cross Reference and Assembler Summary

### OPTEND

Print the Options Summary at the end of the assembler listing, instead of at the beginning.

---

## Messages

ASMAXPRT might issue message ASMA701W as follows:

- \*\* ASMA701W LISTING: ASMAXPRT - Invalid Option Specified: xxxxxxxx

This message is issued because the value *xxxxxxx*, specified as an exit string of the EXIT assembler option, is not recognized by ASMAXPRT.

The exit uses the keyword options processed until the error was detected. Any values in the exit string after *xxxxxxx* are ignored.

- \*\* ASMA701W LISTING: ASMAXPRT - No options specified

This message is issued because ASMAXPRT expects one or more keyword options in the exit string of the EXIT assembler option.

- \*\* ASMA701W LISTING: ASMAXPRT - Exit buffer is full

This message is issued because ASMAXPRT, as supplied, only supports a maximum of 60 lines for the Options Summary page. To increase this value, or change it to allow an unlimited number of lines, modify the exit source then assemble and link-edit it.

This error might cause an incomplete Options Summary page.



---

## Appendix K. Sample SOURCE user exit (z/OS and CMS)

ASMAXINV is a sample SOURCE exit supplied with High Level Assembler.

---

### Function

The sample SOURCE exit reads variable-length source data sets. Each record that is read is passed to the assembler as an 80-byte source statement. If any record in the input data set is longer than 71 characters, the remaining part of the record is converted into continuation records.

The exit also reads a data set with a fixed record length of 80 bytes.

---

### Preparing the exit

Before the exit can be used it must be assembled and link-edited, and the load module (phase) placed in a library in the standard search order. ASMAXINV, as supplied, has the following attributes: reusable, reenterable, amode(24), rmode(24).

Refer to Chapter 4, “Providing user exits,” on page 87 for further information about coding and preparing user exits.

---

### Invoking the exit

To invoke the exit specify the EXIT assembler option as follows:

```
EXIT(INEXIT(ASMAXINV))
```

## Invoking the exit

---

## Appendix L. How to generate a translation table

High Level Assembler uses the EBCDIC character set to represent characters contained in character (C-type) data constants (DCs) and literals. The TRANSLATE assembler option lets you specify a module containing a translation table which the assembler uses to convert these characters into another character set.

High Level Assembler provides an ASCII translation table; however, you can supply your own translation table. The translation table module must be named `ASMALTxx`, where `xx` is the suffix specified in the TRANSLATE assembler option. See “TRANSLATE” on page 79.

---

### Preparing the translation table

The user-supplied translation table must be assembled and link-edited into a library in the standard load module search order. The full name of the translation table load module name must occupy bytes 257 to 264 of the module. The first byte of the module must be the first byte of the translation table.

A sample translation table to convert a subset of EBCDIC characters from code page 500 into ASCII characters from code page 367 is shown in Figure 69 on page 408. Specify the TRANSLATE(U1) assembler option to use this translation table.

---

```

* Translate from EBCDIC Code Page 500 to ASCII Code Page 368.
* Untranslated characters are set to X'00'.
&LT      SETC  'ASMALTU1'
&LT      CSECT
DC        256X'00'
ORG      &LT+64
DC        X'20'          EBCDIC: X'40' space
ORG      &LT+75
DC        X'2E3C282B'    EBCDIC: .<( +
ORG      &LT+80
DC        X'26'          EBCDIC: &
ORG      &LT+90
DC        X'21242A293B'  EBCDIC: !$*);
ORG      &LT+96
DC        X'2D2F'        EBCDIC: -/
ORG      &LT+106
DC        X'7C2C255F3E3F' EBCDIC: |,%_>?
ORG      &LT+121
DC        X'603A2340273D' EBCDIC: `:#@' =
ORG      &LT+127
DC        X'22'          EBCDIC: "
ORG      &LT+129
DC        X'616263646566' EBCDIC: abcdef
ORG      &LT+135
DC        X'676869'      EBCDIC: ghi
ORG      &LT+145
DC        X'6A6B6C6D6E6F' EBCDIC: jklmno
ORG      &LT+151
DC        X'707172'      EBCDIC: pqr
ORG      &LT+159
DC        X'A4'          EBCDIC: X'A4' euro
ORG      &LT+161
DC        X'7E7374757677' EBCDIC: ~stuvw
ORG      &LT+167
DC        X'78797A'      EBCDIC: xyz
ORG      &LT+186
DC        X'5B5D'        EBCDIC: []
ORG      &LT+192
DC        X'7B41424344'  EBCDIC: {ABCD
ORG      &LT+197
DC        X'4546474849'  EBCDIC: EFGHI
ORG      &LT+208
DC        X'7D4A4B4C4D'  EBCDIC: }JKLM
ORG      &LT+213
DC        X'4E4F505152'  EBCDIC: NOPQR
ORG      &LT+224
DC        X'5C'          EBCDIC: \
ORG      &LT+226
DC        X'53545556'    EBCDIC: STUV
ORG      &LT+230
DC        X'5758595A'    EBCDIC: WXYZ
ORG      &LT+240
DC        X'3031323334'  EBCDIC: 01234
ORG      &LT+245
DC        X'3536373839'  EBCDIC: 56789
ORG      &LT+256
DC        CL8'&LT'      Table name = Module name
END

```

---

*Figure 69. Sample Translation Table*

---

## Appendix M. How to generate a Unicode translation table

High Level Assembler supports the definition of EBCDIC SBCS data constants which are converted to Unicode data constants. A Unicode character (CU-type) data constant (DC) is converted to a Unicode DBCS constant using a code page module. This module is identified using the CODEPAGE assembler option (see “CODEPAGE” on page 46). The code page module must be named ASMAxxxx, where xxxx is the value supplied to the CODEPAGE assembler option.

---

### Preparing the Unicode translation table

The user-supplied Unicode translation table must be assembled and link-edited into a library in the standard load module search order.

- The full name of the translation table load module name must occupy bytes 1 to 8 of the module.
- The address of the translation table must be in bytes 65 to 68 of the module.
- The two code pages handled by this translation table must be in bytes 69 to 72 of the module. The number of the “from” code page must be in bytes 69 and 70, and the number of the “to” code page must be in bytes 71 and 72.

A sample Unicode translation table is shown in Figure 69 on page 408. Specify the CODEPAGE(X'FFFF') assembler option to use this translation table.

The first five DCs in this module are an eye-catcher, which is information that is easy to read from a dump. The eye-catcher includes useful information such as the date and time the module was built, and the PTF level.

## Preparing the Unicode translation table

---

```

ASMAFFFF CSECT
ASMAFFFF AMODE 31
ASMAFFFF RMODE ANY
DC      C'ASMAFFFF'      Module name
DC      CL8'&SYSPARM '    PTF
DC      CL8'&SYSDATC'      Date
DC      CL8'&SYSTIME'      Time
DC      CL32'Module Description'
DC      A(UNICODE)        Address of UNICODE translation table
DC      X'47C'            From code page number
DC      X'44B0'           To code page number
DC      CL60              Reserved
UNICODE DS      0H
DC      X'0000'           EBCDIC hexadecimal value 00
DC      X'0001'           EBCDIC hexadecimal value 01
DC      X'0002'           EBCDIC hexadecimal value 02
DC      X'0003'           EBCDIC hexadecimal value 03
DC      X'009C'           EBCDIC hexadecimal value 04
DC      X'0009'           EBCDIC hexadecimal value 05
DC      X'0086'           EBCDIC hexadecimal value 06
DC      X'007F'           EBCDIC hexadecimal value 07
DC      X'0097'           EBCDIC hexadecimal value 08
DC      X'008D'           EBCDIC hexadecimal value 09
DC      X'008E'           EBCDIC hexadecimal value 0A
DC      X'000B'           EBCDIC hexadecimal value 0B
DC      X'000C'           EBCDIC hexadecimal value 0C
DC      X'000D'           EBCDIC hexadecimal value 0D
DC      X'000E'           EBCDIC hexadecimal value 0E
DC      X'000F'           EBCDIC hexadecimal value 0F
DC      X'0010'           EBCDIC hexadecimal value 10
DC      X'0011'           EBCDIC hexadecimal value 11
DC      X'0012'           EBCDIC hexadecimal value 12
DC      X'0013'           EBCDIC hexadecimal value 13
DC      X'009D'           EBCDIC hexadecimal value 14
DC      X'0085'           EBCDIC hexadecimal value 15
DC      X'0008'           EBCDIC hexadecimal value 16
DC      X'0087'           EBCDIC hexadecimal value 17
DC      X'0018'           EBCDIC hexadecimal value 18
DC      X'0019'           EBCDIC hexadecimal value 19
DC      X'0092'           EBCDIC hexadecimal value 1A
DC      X'008F'           EBCDIC hexadecimal value 1B
DC      X'001C'           EBCDIC hexadecimal value 1C
DC      X'001D'           EBCDIC hexadecimal value 1D
DC      X'001E'           EBCDIC hexadecimal value 1E
DC      X'001F'           EBCDIC hexadecimal value 1F
DC      X'0080'           EBCDIC hexadecimal value 20
DC      X'0081'           EBCDIC hexadecimal value 21
DC      X'0082'           EBCDIC hexadecimal value 22
DC      X'0083'           EBCDIC hexadecimal value 23
DC      X'0084'           EBCDIC hexadecimal value 24
DC      X'000A'           EBCDIC hexadecimal value 25
DC      X'0017'           EBCDIC hexadecimal value 26
DC      X'001B'           EBCDIC hexadecimal value 27
DC      X'0088'           EBCDIC hexadecimal value 28
DC      X'0089'           EBCDIC hexadecimal value 29
DC      X'008A'           EBCDIC hexadecimal value 2A
DC      X'008B'           EBCDIC hexadecimal value 2B
DC      X'008C'           EBCDIC hexadecimal value 2C
DC      X'0005'           EBCDIC hexadecimal value 2D
DC      X'0006'           EBCDIC hexadecimal value 2E
DC      X'0007'           EBCDIC hexadecimal value 2F
DC      X'0090'           EBCDIC hexadecimal value 30
DC      X'0091'           EBCDIC hexadecimal value 31
DC      X'0016'           EBCDIC hexadecimal value 32
DC      X'0093'           EBCDIC hexadecimal value 33
DC      X'0094'           EBCDIC hexadecimal value 34
DC      X'0095'           EBCDIC hexadecimal value 35
DC      X'0096'           EBCDIC hexadecimal value 36
DC      X'0004'           EBCDIC hexadecimal value 37

```

---

Figure 70. Sample Unicode translation table (Part 1 of 4)

---

DC	X'0098'	EBCDIC hexadecimal value 38
DC	X'0099'	EBCDIC hexadecimal value 39
DC	X'009A'	EBCDIC hexadecimal value 3A
DC	X'009B'	EBCDIC hexadecimal value 3B
DC	X'0014'	EBCDIC hexadecimal value 3C
DC	X'0015'	EBCDIC hexadecimal value 3D
DC	X'009E'	EBCDIC hexadecimal value 3E
DC	X'001A'	EBCDIC hexadecimal value 3F
DC	X'0020'	EBCDIC hexadecimal value 40
DC	X'00A0'	EBCDIC hexadecimal value 41
DC	X'00E2'	EBCDIC hexadecimal value 42
DC	X'00E4'	EBCDIC hexadecimal value 43
DC	X'00E0'	EBCDIC hexadecimal value 44
DC	X'00E1'	EBCDIC hexadecimal value 45
DC	X'00E3'	EBCDIC hexadecimal value 46
DC	X'00E5'	EBCDIC hexadecimal value 47
DC	X'00E7'	EBCDIC hexadecimal value 48
DC	X'00F1'	EBCDIC hexadecimal value 49
DC	X'005B'	EBCDIC hexadecimal value 4A
DC	X'002E'	EBCDIC hexadecimal value 4B
DC	X'003C'	EBCDIC hexadecimal value 4C
DC	X'0028'	EBCDIC hexadecimal value 4D
DC	X'002B'	EBCDIC hexadecimal value 4E
DC	X'0021'	EBCDIC hexadecimal value 4F
DC	X'0026'	EBCDIC hexadecimal value 50
DC	X'00E9'	EBCDIC hexadecimal value 51
DC	X'00EA'	EBCDIC hexadecimal value 52
DC	X'00EB'	EBCDIC hexadecimal value 53
DC	X'00E8'	EBCDIC hexadecimal value 54
DC	X'00ED'	EBCDIC hexadecimal value 55
DC	X'00EE'	EBCDIC hexadecimal value 56
DC	X'00EF'	EBCDIC hexadecimal value 57
DC	X'00EC'	EBCDIC hexadecimal value 58
DC	X'00DF'	EBCDIC hexadecimal value 59
DC	X'005D'	EBCDIC hexadecimal value 5A
DC	X'0024'	EBCDIC hexadecimal value 5B
DC	X'002A'	EBCDIC hexadecimal value 5C
DC	X'0029'	EBCDIC hexadecimal value 5D
DC	X'003B'	EBCDIC hexadecimal value 5E
DC	X'005E'	EBCDIC hexadecimal value 5F
DC	X'002D'	EBCDIC hexadecimal value 60
DC	X'002F'	EBCDIC hexadecimal value 61
DC	X'00C2'	EBCDIC hexadecimal value 62
DC	X'00C4'	EBCDIC hexadecimal value 63
DC	X'00C0'	EBCDIC hexadecimal value 64
DC	X'00C1'	EBCDIC hexadecimal value 65
DC	X'00C3'	EBCDIC hexadecimal value 66
DC	X'00C5'	EBCDIC hexadecimal value 67
DC	X'00C7'	EBCDIC hexadecimal value 68
DC	X'00D1'	EBCDIC hexadecimal value 69
DC	X'00A6'	EBCDIC hexadecimal value 6A
DC	X'002C'	EBCDIC hexadecimal value 6B
DC	X'0025'	EBCDIC hexadecimal value 6C
DC	X'005F'	EBCDIC hexadecimal value 6D
DC	X'003E'	EBCDIC hexadecimal value 6E
DC	X'003F'	EBCDIC hexadecimal value 6F
DC	X'00F8'	EBCDIC hexadecimal value 70
DC	X'00C9'	EBCDIC hexadecimal value 71
DC	X'00CA'	EBCDIC hexadecimal value 72
DC	X'00CB'	EBCDIC hexadecimal value 73
DC	X'00C8'	EBCDIC hexadecimal value 74
DC	X'00CD'	EBCDIC hexadecimal value 75
DC	X'00CE'	EBCDIC hexadecimal value 76
DC	X'00CF'	EBCDIC hexadecimal value 77
DC	X'00CC'	EBCDIC hexadecimal value 78
DC	X'0060'	EBCDIC hexadecimal value 79
DC	X'003A'	EBCDIC hexadecimal value 7A
DC	X'0023'	EBCDIC hexadecimal value 7B
DC	X'0040'	EBCDIC hexadecimal value 7C

---

Figure 70. Sample Unicode translation table (Part 2 of 4)

## Preparing the Unicode translation table

---

DC	X'0027'	EBCDIC hexadecimal value 7D
DC	X'003D'	EBCDIC hexadecimal value 7E
DC	X'0022'	EBCDIC hexadecimal value 7F
DC	X'00D8'	EBCDIC hexadecimal value 80
DC	X'0061'	EBCDIC hexadecimal value 81
DC	X'0062'	EBCDIC hexadecimal value 82
DC	X'0063'	EBCDIC hexadecimal value 83
DC	X'0064'	EBCDIC hexadecimal value 84
DC	X'0065'	EBCDIC hexadecimal value 85
DC	X'0066'	EBCDIC hexadecimal value 86
DC	X'0067'	EBCDIC hexadecimal value 87
DC	X'0068'	EBCDIC hexadecimal value 88
DC	X'0069'	EBCDIC hexadecimal value 89
DC	X'00AB'	EBCDIC hexadecimal value 8A
DC	X'00BB'	EBCDIC hexadecimal value 8B
DC	X'00F0'	EBCDIC hexadecimal value 8C
DC	X'00FD'	EBCDIC hexadecimal value 8D
DC	X'00FE'	EBCDIC hexadecimal value 8E
DC	X'00B1'	EBCDIC hexadecimal value 8F
DC	X'00B0'	EBCDIC hexadecimal value 90
DC	X'006A'	EBCDIC hexadecimal value 91
DC	X'006B'	EBCDIC hexadecimal value 92
DC	X'006C'	EBCDIC hexadecimal value 93
DC	X'006D'	EBCDIC hexadecimal value 94
DC	X'006E'	EBCDIC hexadecimal value 95
DC	X'006F'	EBCDIC hexadecimal value 96
DC	X'0070'	EBCDIC hexadecimal value 97
DC	X'0071'	EBCDIC hexadecimal value 98
DC	X'0072'	EBCDIC hexadecimal value 99
DC	X'00AA'	EBCDIC hexadecimal value 9A
DC	X'00BA'	EBCDIC hexadecimal value 9B
DC	X'00E6'	EBCDIC hexadecimal value 9C
DC	X'00B8'	EBCDIC hexadecimal value 9D
DC	X'00C6'	EBCDIC hexadecimal value 9E
DC	X'20AC'	EBCDIC hexadecimal value 9F
DC	X'00B5'	EBCDIC hexadecimal value A0
DC	X'007E'	EBCDIC hexadecimal value A1
DC	X'0073'	EBCDIC hexadecimal value A2
DC	X'0074'	EBCDIC hexadecimal value A3
DC	X'0075'	EBCDIC hexadecimal value A4
DC	X'0076'	EBCDIC hexadecimal value A5
DC	X'0077'	EBCDIC hexadecimal value A6
DC	X'0078'	EBCDIC hexadecimal value A7
DC	X'0079'	EBCDIC hexadecimal value A8
DC	X'007A'	EBCDIC hexadecimal value A9
DC	X'00A1'	EBCDIC hexadecimal value AA
DC	X'00BF'	EBCDIC hexadecimal value AB
DC	X'00D0'	EBCDIC hexadecimal value AC
DC	X'00DD'	EBCDIC hexadecimal value AD
DC	X'00DE'	EBCDIC hexadecimal value AE
DC	X'00AE'	EBCDIC hexadecimal value AF
DC	X'00A2'	EBCDIC hexadecimal value B0
DC	X'00A3'	EBCDIC hexadecimal value B1
DC	X'00A5'	EBCDIC hexadecimal value B2
DC	X'00B7'	EBCDIC hexadecimal value B3
DC	X'00A9'	EBCDIC hexadecimal value B4
DC	X'00A7'	EBCDIC hexadecimal value B5
DC	X'00B6'	EBCDIC hexadecimal value B6
DC	X'00BC'	EBCDIC hexadecimal value B7
DC	X'00BD'	EBCDIC hexadecimal value B8
DC	X'00BE'	EBCDIC hexadecimal value B9
DC	X'00AC'	EBCDIC hexadecimal value BA
DC	X'007C'	EBCDIC hexadecimal value BB
DC	X'00AF'	EBCDIC hexadecimal value BC
DC	X'00A8'	EBCDIC hexadecimal value BD
DC	X'00B4'	EBCDIC hexadecimal value BE
DC	X'00D7'	EBCDIC hexadecimal value BF
DC	X'007B'	EBCDIC hexadecimal value C0
DC	X'0041'	EBCDIC hexadecimal value C1

---

Figure 70. Sample Unicode translation table (Part 3 of 4)



---

DC	X'0042'	EBCDIC hexadecimal value C2
DC	X'0043'	EBCDIC hexadecimal value C3
DC	X'0044'	EBCDIC hexadecimal value C4
DC	X'0045'	EBCDIC hexadecimal value C5
DC	X'0046'	EBCDIC hexadecimal value C6
DC	X'0047'	EBCDIC hexadecimal value C7
DC	X'0048'	EBCDIC hexadecimal value C8
DC	X'0049'	EBCDIC hexadecimal value C9
DC	X'00AD'	EBCDIC hexadecimal value CA
DC	X'00F4'	EBCDIC hexadecimal value CB
DC	X'00F6'	EBCDIC hexadecimal value CC
DC	X'00F2'	EBCDIC hexadecimal value CD
DC	X'00F3'	EBCDIC hexadecimal value CE
DC	X'00F5'	EBCDIC hexadecimal value CF
DC	X'007D'	EBCDIC hexadecimal value D0
DC	X'004A'	EBCDIC hexadecimal value D1
DC	X'004B'	EBCDIC hexadecimal value D2
DC	X'004C'	EBCDIC hexadecimal value D3
DC	X'004D'	EBCDIC hexadecimal value D4
DC	X'004E'	EBCDIC hexadecimal value D5
DC	X'004F'	EBCDIC hexadecimal value D6
DC	X'0050'	EBCDIC hexadecimal value D7
DC	X'0051'	EBCDIC hexadecimal value D8
DC	X'0052'	EBCDIC hexadecimal value D9
DC	X'00B9'	EBCDIC hexadecimal value DA
DC	X'00FB'	EBCDIC hexadecimal value DB
DC	X'00FC'	EBCDIC hexadecimal value DC
DC	X'00F9'	EBCDIC hexadecimal value DD
DC	X'00FA'	EBCDIC hexadecimal value DE
DC	X'00FF'	EBCDIC hexadecimal value DF
DC	X'005C'	EBCDIC hexadecimal value E0
DC	X'00F7'	EBCDIC hexadecimal value E1
DC	X'0053'	EBCDIC hexadecimal value E2
DC	X'0054'	EBCDIC hexadecimal value E3
DC	X'0055'	EBCDIC hexadecimal value E4
DC	X'0056'	EBCDIC hexadecimal value E5
DC	X'0057'	EBCDIC hexadecimal value E6
DC	X'0058'	EBCDIC hexadecimal value E7
DC	X'0059'	EBCDIC hexadecimal value E8
DC	X'005A'	EBCDIC hexadecimal value E9
DC	X'00B2'	EBCDIC hexadecimal value EA
DC	X'00D4'	EBCDIC hexadecimal value EB
DC	X'00D6'	EBCDIC hexadecimal value EC
DC	X'00D2'	EBCDIC hexadecimal value ED
DC	X'00D3'	EBCDIC hexadecimal value EE
DC	X'00D5'	EBCDIC hexadecimal value EF
DC	X'0030'	EBCDIC hexadecimal value F0
DC	X'0031'	EBCDIC hexadecimal value F1
DC	X'0032'	EBCDIC hexadecimal value F2
DC	X'0033'	EBCDIC hexadecimal value F3
DC	X'0034'	EBCDIC hexadecimal value F4
DC	X'0035'	EBCDIC hexadecimal value F5
DC	X'0036'	EBCDIC hexadecimal value F6
DC	X'0037'	EBCDIC hexadecimal value F7
DC	X'0038'	EBCDIC hexadecimal value F8
DC	X'0039'	EBCDIC hexadecimal value F9
DC	X'00B3'	EBCDIC hexadecimal value FA
DC	X'00DB'	EBCDIC hexadecimal value FB
DC	X'00DC'	EBCDIC hexadecimal value FC
DC	X'00D9'	EBCDIC hexadecimal value FD
DC	X'00DA'	EBCDIC hexadecimal value FE
DC	X'009F'	EBCDIC hexadecimal value FF
END		

---

Figure 70. Sample Unicode translation table (Part 4 of 4)



---

## Appendix N. TYPECHECK assembler option

You can use the TYPECHECK option to control whether or not the assembler performs type checking of machine instruction operands.

TYPECHECK has suboptions to enable or disable different type checking behavior:

### TYPECHECK(MAGNITUDE|NOMAGNITUDE)

Specifies that the assembler performs (or does not perform) magnitude validation of signed immediate-data fields of machine instruction operands.

### TYPECHECK(REGISTER|NOREGISTER)

Specifies that the assembler performs (or does not perform) type checking of register fields of machine instruction operands.

**Note:** For details about the syntax for the TYPECHECK option, see “TYPECHECK” on page 79.

For fine control, the TYPECHECK option is also supported on the PROCESS, ACONTROL, PUSH, and POP assembler instructions.

---

## Extensions to the DC, DS, and EQU assembler instructions

The symbol table allows each symbol to have a program type and an assembler type assigned.

The DC and DS assembler instructions allow you to specify a program type in the fourth subfield, following type\_extension.

The subfield has the format P(*program\_type*), where *program\_type* is a 32 bit self-defining term. For example:

```
Honda    DC    HP(C'Car')'13'
Nissan    DC    HP(C'Car')'32'
Kenworth DC    FP(C'Truk')'128'
Mack      DC    FDP(C'Truk')'101'
```

The assembler assigns a default assembler type to the symbol comprising the type\_user subfield and, if specified, the type\_extension subfield.

The EQU assembler instruction allows you to specify a program type operand and an assembler type operand.

You use the fourth operand (program type) to specify a 32-bit self-defining term. This value is assigned as the symbol’s program type. For example:

```
Payment    EQU    13,,,C'Rate'
Bonus      EQU    42,,,12345
```

You use the fifth operand (assembler type) to specify an assembler type keyword, which is restricted to a specific set of keywords. For a list of valid keywords for the EQU instruction, see “EQU instruction” in the *HLASM Language Reference*. The value (1 to 4 bytes) is assigned as the symbol’s assembler type.

For example:

## Extensions to the DC, DS, and EQU assembler instructions

```
|          R9          EQU    9,,,,FPR
|          R10         EQU    10,,,,GR
|          R11         EQU    11,,,,GR
```

The SYSATTRP built-in function allows you to query the program type for a symbol. The SYSATTRA built-in function allows you to query the assembler type for a symbol.

For details about the DC, DS, and EQU instructions, or the SYSATTRP and SYSATTRA built-in functions, see the *HLASM Language Reference*.

Figure 71 shows the behavior using T' and built-in functions to retrieve the original type attribute, the program type, and the assembler type for a DC symbol. Also shown is the extended DC instruction allowing the assigning of the program type to the defined symbol.

---

```
Macro
&Lab      Show_Types &Symbol
&Original_Type SetC T'&Symbol
&Program_Type SetC SYSATTRP('&Symbol')
&Assembler_Type SetC SYSATTRA('&Symbol')
          MNote 0,'Type Attribute via T' is '&Original_Type.'.'
          MNote 0,'Program Type via function is '&Program_Type.'.'
          MNote 0,'Assembler Type via function is '&Assembler_Type.'.'
          MEnd
*
Show1     Show_Types Increment
+         0,'Type Attribute via T' is 'F'.
+         0,'Program Type via function is 'Mony'.
+         0,'Assembler Type via function is 'F'.
Show2     Show_Types PayRate
+         0,'Type Attribute via T' is 'F'.
+         0,'Program Type via function is 'Mony'.
+         0,'Assembler Type via function is 'FD'.
*
Increment DC  FP(C'Mony')'3'
PayRate   DC  FDP(C'Mony')'42'
```

---

Figure 71. Behavior to assign and retrieve a symbol's types

Figure 72 on page 417 shows the behavior using T' and built-in functions to retrieve the original type attribute, the program type, and the assembler type for an EQU symbol. Also shown is the EQU instruction allowing the assigning of assembler types to symbols used to represent registers.

---

```

Macro
&Lab      Show_Types &Symbol
&Original_Type SetC T'&Symbol
&Program_Type SetC SYSATTRP('&Symbol')
&Assembler_Type SetC SYSATTRA('&Symbol')
MNote 0,'Type Attribute via T' is '&Original_Type.'.'
MNote 0,'Program Type via function is '&Program_Type.'.'
MNote 0,'Assembler Type via function is '&Assembler_Type.'.'
MEnd

*
Show1 Show_Types R0
+ 0,Type Attribute via T' is 'U'.
+ 0,Program Type via function is 'Work'.
+ 0,Assembler Type via function is 'GR'.
Show2 Show_Types R1
+ 0,Type Attribute via T' is 'U'.
+ 0,Program Type via function is ''.
+ 0,Assembler Type via function is 'GR32'.
Show3 Show_Types A12
+ 0,Type Attribute via T' is 'U'.
+ 0,Program Type via function is ''.
+ 0,Assembler Type via function is 'AR'.
Show4 Show_Types FP4
+ 0,Type Attribute via T' is 'U'.
+ 0,Program Type via function is 'Spam'.
+ 0,Assembler Type via function is 'FPR'.
*
R0 EQU 0,,,'C'Work',GR
R1 EQU 1,,,'GR32'
A12 EQU 12,,,'AR'
FP4 EQU 4,,,'C'Rate',FPR

```

---

Figure 72. Behavior to assign and retrieve a symbol's register types

## Type checking behavior for REGISTER

Type checking for REGISTER cause the assembler to perform type checking of register fields of machine instruction operands.

As described previously in “Extensions to the DC, DS, and EQU assembler instructions” on page 415, you can use the EQU assembler instruction to specify assembler types to be assigned to a symbol. The assembler types apply to registers. The REGISTER suboption (the default) controls whether the assembler uses these assembler types. To disable the checking, use the NOREGISTER suboption.

When it is resolving register fields of machine instructions, the assembler uses the machine instruction format, expected operand format, and expected operand length, to check for acceptable types on any symbols specified as register operands or register parts of operands.

The assembler maintains flags which track when one or more instances of a specific register assembler type has been encountered on an EQU instruction in the source code. The assembler uses these flags to decide on the depth of register type checking for that piece of source code.

The description and examples in the remainder of this section assume that checking is active, and describe assembler behavior when machine instruction register fields of specific types are being evaluated.

## Access Register type checking

The following examples use the Load Access Multiple (LAM) instruction and are only concerned with the access register fields. The first and second operands are register fields requiring a resolved absolute value of 0 through to 15. This value specifies an Access Register (AR).

Each unresolved access register field may be an expression comprised of one or more terms. The assembler checks only the first term as follows:

- If the term is not a symbol, no more checking is performed.
- If the assembler type of the symbol is AR, no more checking is performed
- If the assembler type of the symbol is assigned but is not AR, the assembler issues a warning message (severity 4) about a type checking conflict.
- If the assembler type of the symbol is not assigned, and the flag shows that at least one instance of an EQU statement with AR has been encountered, the assembler issues an informational message (severity 0) about a possible type checking conflict.
- If the assembler type of the symbol is not assigned, and the flag shows that no instances of an EQU statement with AR have been encountered, no more checking is performed.

Figure 73 shows an example of Access Register checking, with warning messages about incompatible symbol types, and an informational message about a symbol not assigned an assembler type due to the existence of an EQU statement with AR in the source code.

---

00000000 9AEC D00C	0000000C	30	LAM	14,12,12(13)
00000004 9AEC D00C	0000000C	31	LAM	A14,A12,12(R13)
00000008 9AEC D00C	0000000C	32	LAM	R14,R12,12(R13)
** ASMA323W Symbol 'R14' has incompatible type with access register field				
** ASMA323W Symbol 'R12' has incompatible type with access register field				
0000000C 9AEC D00C	0000000C	33	LAM	AR14,A12,12(R13)
** ASMA324I Symbol 'AR14' may have incompatible type with access register field				
		34	*	
	0000000C	35	A12	EQU 12,,,AR
	0000000E	36	A14	EQU 14,,,AR
		37	*	
	0000000C	38	R12	EQU 12,,,GR
	0000000D	39	R13	EQU 13,,,GR
	0000000E	40	R14	EQU 14,,,GR
		41	*	
	0000000C	42	AR12	EQU 12
	0000000E	43	AR14	EQU 14

---

Figure 73. Access Register type checking with AR activated

Figure 74 on page 419 shows an example of Access Register checking, with warning messages of incompatible symbol types, and tolerance of symbols not assigned an assembler type due to the lack of an EQU statement with AR in the source code.

00000000 9AEC D00C	0000000C	30	LAM	14,12,12(13)
00000004 9AEC D00C	0000000C	31	LAM	A14,A12,12(R13)
00000008 9AEC D00C	0000000C	32	LAM	R14,R12,12(R13)
** ASMA323W Symbol R14 has incompatible type with access register field				
** ASMA323W Symbol R12 has incompatible type with access register field				
0000000C 9AEC D00C	0000000C	33	LAM	AR14,A12,12(R13)
		34 *		
	0000000C	35 A12	EQU	12
	0000000E	36 A14	EQU	14
		37 *		
	0000000C	38 R12	EQU	12,,,,GR
	0000000D	39 R13	EQU	13,,,,GR
	0000000E	40 R14	EQU	14,,,,GR
		41 *		
	0000000C	42 AR12	EQU	12
	0000000E	43 AR14	EQU	14

Figure 74. Access Register type checking with AR inactive

## General Register type checking

The following examples use two instructions and are only concerned with the general register fields:

- The Load (L) instruction in which the first operand is a register field requiring a resolved absolute value of 0 through to 15. This value specifies a General Register (GR) which is treated as a 32-bit General Register (GR32).
- The Load (LG) instruction in which the first operand is a register field requiring a resolved absolute value of 0 through to 15. This value specifies a General Register (GR) which is treated as a 64-bit General Register (GR64).

Assembler type GR can normally be used for both the L and LG instructions, unless symbols have been defined with types of GR32 or GR64. Once use is made of the 32-bit or 64-bit types for general registers, then the assembler becomes more restrictive in its checking. This could be helpful when you are programming for a mix of hardware architectures, or converting code from 32-bit to 64-bit hardware.

Each unresolved general register field may be an expression comprised of one or more terms. The assembler checks only the first term as follows for the L instruction:

- If the term is not a symbol, no more checking is performed.
- If the assembler type of the symbol is GR32, no more checking is performed
- If the assembler type of the symbol is GR, and the flag shows that at least one instance of an EQU statement with GR32 has been encountered, the assembler issues an informational message (severity 0) about a possible type checking conflict.
- If the assembler type of the symbol is assigned but is not GR or GR32, the assembler issues a warning message (severity 4) about a type checking conflict.
- If the assembler type of the symbol is not assigned, and the flags show that at least one instance of an EQU with GR or GR32 has been encountered, the assembler issues an informational message (severity 0) about a possible type checking conflict.
- If the assembler type of the symbol is not assigned, and if the flags show that no instances of an EQU with GR or GR32 have been encountered, no more checking is performed.

## Type checking behavior for REGISTER

Each unresolved general register field may be an expression comprised of one or more terms. The assembler checks only the first term as follows for the LG instruction:

- If the term is not a symbol, no more checking is performed.
- If the assembler type of the symbol is GR64, no more checking is performed.
- If the assembler type of the symbol is GR, and the flag shows that at least one instance of an EQU with GR64 has been encountered, the assembler issues an informational message (severity 0) about a possible type checking conflict.
- If the assembler type of the symbol is assigned, but is not GR or GR64, the assembler issues a warning message (severity 4) about a type checking conflict.
- If the assembler type of the symbol is not assigned, and if the flags show that at least one instance of an EQU with GR or GR64 has been encountered, the assembler issues an informational message (severity 0) about a possible type checking conflict.
- If the assembler type of the symbol is not assigned, and if the flags show that no instances of an EQU with GR or GR64 have been encountered, no more checking is performed.

Figure 75 shows an example of General Register checking, with a warning message about an incompatible symbol type, and an informational message about a symbol not assigned an assembler type due to the existence of an EQU statement with GR in the source code.

---

00000000	5824	C000	00000000	30	L	2,0(4,12)
00000004	5824	C000	00000000	31	L	R2,0(R4,R12)
00000008	5824	C000	00000000	32	L	A2,0(R4,R12)
** ASMA323W Symbol A2 has incompatible type with general register field						
0000000C	5824	C000	00000000	33	L	REG2,0(R4,R12)
** ASMA324I Symbol REG2 may have incompatible type with general register field						
00000010	E324	C000 0004	00000000	34	LG	R2,0(R4,R12)
				35	*	
		00000002		36	R2	EQU 2,,,GR
		00000004		37	R4	EQU 4,,,GR
		0000000C		38	R12	EQU 12,,,GR
				39	*	
		00000002		40	A2	EQU 2,,,AR
				41	*	
		00000002		42	REG2	EQU 2

---

Figure 75. General Register type checking with GR activated

Figure 76 on page 421 shows an example of General Register checking, with a warning message about an incompatible symbol type, and tolerance of symbols not assigned an assembler type due to the lack of an EQU statement with GR in the source code.



---

```

00000000 5824 C000          00000000 30      L    2,0(4,12)
00000004 5824 C000          00000000 31      L    R2,0(R4,R12)
00000008 5824 C000          00000000 32      L    A2,0(R4,R12)
** ASMA323W Symbol A2 has incompatible type with general register field
0000000C 5824 C000          00000000 33      L    REG2,0(R4,R12)
00000010 E334 C000 0004      00000000 34      LG   R3,0(R4,R12)
                                35 *
                                36 R2      EQU   2
                                37 R3      EQU   3
                                38 R4      EQU   4
                                39 R12     EQU   12
                                40 *
                                41 A2      EQU   2,,,AR
                                42 *
                                43 REG2    EQU   2

```

---

Figure 76. General Register type checking with GR inactive

Figure 77 shows an example of General Register checking, with an informational message about a symbol with a GR assembler type due to the existence of an EQU statement with GR32 in the source code, and a warning message about an incompatible symbol type.

---

```

00000000 5824 C000          00000000 31      L    R2,0(R4,R12)
** ASMA324I Symbol R2 may have incompatible type with general register field
00000004 E334 C000 0004      00000000 32      LG   R3,0(R4,R12)
** ASMA323W Symbol R3 has incompatible type with general register field
0000000A E324 C000 0004      00000000 33      LG   R2,0(R4,R12)
                                34 *
                                35 R2      EQU   2,,,GR
                                36 R3      EQU   3,,,GR32
                                37 R4      EQU   4,,,GR
                                38 R12     EQU   12,,,GR

```

---

Figure 77. General Register type checking with GR32 activated

Figure 78 shows an example of General Register checking, with informational messages about symbols with a GR assembler type due to the existence of both an EQU statement with GR32 and an EQU statement with GR64 in the source code, and a warning message about an incompatible symbol type.

---

```

00000000 5824 C000          00000000 31      L    R2,0(R4,R12)
** ASMA324I Symbol R2 may have incompatible type with general register field
00000004 E334 C000 0004      00000000 32      LG   R3,0(R4,R12)
** ASMA323W Symbol R3 has incompatible type with general register field
0000000A E324 C000 0004      00000000 33      LG   R2,0(R4,R12)
** ASMA324I Symbol R2 may have incompatible type with general register field
                                34 *
                                35 R2      EQU   2,,,GR
                                36 R3      EQU   3,,,GR32
                                37 R4      EQU   4,,,GR
                                38 R5      EQU   5,,,GR64
                                39 R12     EQU   12,,,GR

```

---

Figure 78. General Register type checking with GR32 and GR64 activated

## Control Register type checking

The following examples use two instructions and are only concerned with the control register fields:

## Type checking behavior for REGISTER

- The Load Control (LCTL) instruction, in which the first and second operands are register fields requiring a resolved absolute value of 0 through to 15. This value specifies a Control Register (CR) which is treated as a 32-bit Control Register.
- The Load Control (LCTLG) instruction, in which the first and second operands are register fields requiring a resolved absolute value of 0 through to 15. This value specifies a Control Register (CR) which is treated as a 64-bit Control Register.

Each unresolved control register field may be an expression comprised of one or more terms. The assembler checks only the first term as follows:

- If the term is not a symbol, no more checking is performed.
- If the assembler type of the symbol is CR, no more checking is performed.
- If the assembler type of the symbol is assigned but is not CR, the assembler issues a warning message (severity 4) about a type checking conflict.
- If the assembler type of the symbol is not assigned, and if the flags show that at least one instance of an EQU with CR has been encountered, the assembler issues an informational message (severity 0) about a possible type checking conflict.
- If the assembler type of the symbol is not assigned, and if the flags show that no instances of an EQU with CR have been encountered, no more checking is performed.

Figure 79 shows an example of Control Register checking, with a warning message about an incompatible symbol type, and an informational message about a symbol not assigned an assembler type due to the existence of an EQU statement with CR in the source code.

---

00000000 B7EC A00C	0000000C	30	LCTL	14,12,12(10)
00000004 B7EC A00C	0000000C	31	LCTL	C14,C12,12(R10)
00000008 B72C A00C	0000000C	32	LCTL	A2,C12,12(R10)
** ASMA323W Symbol A2 has incompatible type with control register field				
0000000C B7E1 A00C	0000000C	33	LCTL	C14,CON1,12(R10)
** ASMA324I Symbol CON1 may have incompatible type with control register field				
00000010 EBEC A00C 002F	0000000C	34	LCTLG	C14,C12,12(R10)
		35	*	
	0000000C	36	C12	EQU 12,,,CR
	0000000E	37	C14	EQU 14,,,CR
		38	*	
	0000000A	39	R10	EQU 10,,,GR
	00000002	40	A2	EQU 2,,,AR
	00000001	41	CON1	EQU 1

---

Figure 79. Control Register type checking with CR activated

Figure 80 on page 423 shows an example of Control Register checking, with a warning message about an incompatible symbol type, and tolerance of symbols not assigned an assembler type due to the lack of an EQU statement with CR in the source code.

---

00000000 B7EC A00C	0000000C	30	LCTL	14,12,12(10)
00000004 B7EC A00C	0000000C	31	LCTL	C14,C12,12(R10)
00000008 B72C A00C	0000000C	32	LCTL	A2,C12,12(R10)
** ASMA323W Symbol A2 has incompatible type with control register field				
0000000C B7E1 A00C	0000000C	33	LCTL	C14,CON1,12(R10)
00000010 EBEC A00C 002F	0000000C	34	LCTLG	C14,C12,12(R10)
		35 *		
	0000000C	36 C12	EQU	12
	0000000E	37 C14	EQU	14
		38 *		
	0000000A	39 R10	EQU	10,,,GR
	00000002	40 A2	EQU	2,,,AR
	00000001	41 CON1	EQU	1

---

Figure 80. Control Register type checking with CR inactive

## Floating-Point Register type checking

The following examples use two instructions and are only concerned with the floating-point register fields:

- The first operand of the Load Short (LE) instruction is a register field requiring a resolved absolute value of 0 through to 15. This value specifies a Floating-Point Register (FPR).
- The first operand of the Load Long (LD) instruction is a register field requiring a resolved absolute value of 0 through to 15. This value specifies a Floating-Point Register (FPR).

Each unresolved floating-point register field may be an expression comprised of one or more terms. The assembler checks only the first term as follows:

- If the term is not a symbol, no more checking is performed.
- If the assembler type of the symbol is FPR, no more checking is performed.
- If the assembler type of the symbol is assigned but is not FPR, the assembler issues a warning message (severity 4) about a type checking conflict.
- If the assembler type of the symbol is not assigned, and if the flag shows that at least one instance of an EQU with FPR has been encountered, the assembler issues an informational message (severity 0) about a possible type checking conflict.
- If the assembler type of the symbol is not assigned, and if the flag shows that no instances of an EQU with FPR have been encountered, no more checking is performed.

Figure 81 on page 424 shows an example of Floating-Point Register checking, with a warning message about an incompatible symbol type, and an informational message about a symbol not assigned an assembler type due to the existence of an EQU statement with FPR in the source code.

## Type checking behavior for REGISTER

```
00000000 7845 C00C      0000000C  30      LE  4,12(5,12)
00000004 7845 C00C      0000000C  31      LE  FP4,12(R5,R12)
00000008 6825 C00C      0000000C  32      LD  A2,12(R5,R12)
** ASMA323W Symbol A2 has incompatible type with floating-point register field
0000000C 6865 C00C      0000000C  33      LD  FP6,12(R5,R12)
** ASMA324I Symbol FP6 may have incompatible type with floating-point register field
                                34 *
                                35 FP4      EQU  4,,,FPR
                                36 FP6      EQU  6
                                37 *
                                38 R5       EQU  5,,,GR
                                39 R12      EQU  12,,,GR
                                40 A2       EQU  2,,,AR
```

Figure 81. Floating-Point Register type checking with FPR activated

Figure 82 shows an example of Floating-Point Register checking, with a warning message about an incompatible symbol type, and tolerance of symbols not assigned an assembler type due to the lack of an EQU statement with FPR in the source code.

```
00000000 7845 C00C      0000000C  30      LE  4,12(5,12)
00000004 7845 C00C      0000000C  31      LE  FP4,12(R5,R12)
00000008 6825 C00C      0000000C  32      LD  A2,12(R5,R12)
** ASMA323W Symbol A2 has incompatible type with floating-point register field
0000000C 6865 C00C      0000000C  33      LD  FP6,12(R5,R12)
                                34 *
                                35 FP4      EQU  4
                                36 FP6      EQU  6
                                37 *
                                38 R5       EQU  5,,,GR
                                39 R12      EQU  12,,,GR
                                40 A2       EQU  2,,,AR
```

Figure 82. Floating-Point Register type checking with FPR inactive

## Type checking behavior for MAGNITUDE

Type checking for MAGNITUDE causes the assembler to perform magnitude validation of signed immediate-data fields of machine instruction operands. To disable the checking, use the NOMAGNITUDE suboption.

For each violation, a warning message (severity 4) is issued and object code is created.

For a 16-bit signed immediate-data field, the normal allowed range of values is -32768 through to 32767.

For a 32-bit signed immediate-data field, the normal allowed range of values is -2147483648 through to 2147483647.

Figure 83 on page 425 shows the assembler behavior, with the default of MAGNITUDE, which is to issue a warning message and to generate the object code.

---

```

00000000 A72A 8000          00008000    12      AHI      R2,32768
** ASMA320W Immediate field operand may have incorrect sign or magnitude
00000004 A72A 7FFF          00007FFF    13      AHI      R2,32767
00000008 A72A 0001          00000001    14      AHI      R2,1
0000000C A72A 0000          00000000    15      AHI      R2,0
00000010 A72A FFFF          FFFFFFFF    16      AHI      R2,-1
00000014 A72A 8000          FFFF8000    17      AHI      R2,-32768
00000018 A72A 7FFF          FFFF7FFF    18      AHI      R2,-32769
** ASMA320W Immediate field operand may have incorrect sign or magnitude
0000001C A72A FFFF          0000FFFF    19      AHI      R2,X'FFFF'
** ASMA320W Immediate field operand may have incorrect sign or magnitude

```

---

Figure 83. MAGNITUDE behavior

**Note:** When generating object code, the assembler takes bits 16 to 31 of *Addr2* for use as the immediate-data field. Bits 0 to 15 are ignored.

Figure 84 shows the assembler behavior, with NOMAGNITUDE, which is to issue no messages and to generate the object code.

---

```

00000000 A72A 8000          00008000    12      AHI      R2,32768
00000004 A72A 7FFF          00007FFF    13      AHI      R2,32767
00000008 A72A 0001          00000001    14      AHI      R2,1
0000000C A72A 0000          00000000    15      AHI      R2,0
00000010 A72A FFFF          FFFFFFFF    16      AHI      R2,-1
00000014 A72A 8000          FFFF8000    17      AHI      R2,-32768
00000018 A72A 7FFF          FFFF7FFF    18      AHI      R2,-32769
0000001C A72A FFFF          0000FFFF    19      AHI      R2,X'FFFF'

```

---

Figure 84. NOMAGNITUDE behavior

**Note:** When generating object code, the assembler takes bits 16 to 31 of *Addr2* for use as the immediate-data field. Bits 0 to 15 are ignored.



---

## Appendix O. HLASM Services Interface

This section describes in detail the workings of the HLASM Services Interface.

---

### Communication and work areas

The interface between High Level Assembler and its I/O exits establishes a “coroutine” interaction: both the assembler and the exit routine must cooperate, with neither being fully in control of the other. All interactions take place through the I/O exit parameter list. This list is described in more detail in “Exit parameter list” on page 90.

The actions to be taken by the exit and the assembler are determined by the values of the request type (when the assembler calls the exit) and the return and reason code (when the exit returns to the assembler)

The I/O exit interface uses standard OS linkage conventions, and the parameter list follows standard OS parameter-passing conventions. (In fact, this interface is designed to allow exit routines to be written in most high-level languages.) The high-order bit of the last pointer in the I/O exit parameter list is set to 1.

When the HLASM Services Interface is present, the seventh parameter of the I/O exit parameter list (the HLASM Services Interface pointer) points to the HLASM Services Interface block, illustrated in Figure 85 on page 428. The high-order bit of this parameter pointer is set to 1.

C'HSIB'	HLASM Services Interface Block Identifier
HSI block version	Version number of this block
HSI block length	Length of this block
↑ Service entry point	A(Services entry point in HLASM)
↑ Work area	A(work area provided by HLASM)
Number of argument words	Number of argument words for the service
Number of value words	Number of returned-value words for the service
Request type	Type of request
Return code	Return code from the HLASM service
Reserved (3)	Reserved (3 words)
Argument 1	Argument word 1
:	:
Argument 10	Argument word 10
Returned value 1	Returned-value word 1
:	:
Returned value 10	Returned-value word 10

*Figure 85. HLASM Services Interface Block*

The fields in the HLASM Services Interface Block are set by different means:

- The first five fields (fields 1 to 5) are initialized by HLASM before invoking an exit.
- The next three fields (fields 6 to 8) are set by the service requester.
- Field 9 is set by the HLASM Services Interface depending on the status of the request.
- Field 10 and on are set by the the service requester or by the HLASM Services Interface.

The fields in the HLASM Services Interface Block are:

1. HLASM Services Interface block identifier: the EBCDIC characters 'HSIB'.
2. HLASM Services Interface block version. Currently, this is set to 1.
3. HLASM Services Interface block length.
4. The address of the entry point in HLASM that services requests made by way of the HLASM Services Interface block.
5. The address of a 32-byte doubleword-aligned work area provided by HLASM for the use of the service requester.  
These first five fields are initialized by HLASM before invoking an exit or external function. The next three fields are set by the service requester.
6. The number of argument words. Their number and contents is described below for each supported service. The maximum number of argument words for this version of the HLASM Services Interface block is 10.



7. The number of returned-value words. Their number and contents is described below for each supported service. The maximum number of returned-value words for this version of the HLASM Services Interface block is 10. This value is set by HLASM.
8. The type of service request:
  - a. Get storage service (see “Get storage service”)
  - b. Return storage service (see “Return storage service” on page 430)
  - c. Time and date service (see “Time and date service” on page 430)
  - d. Write-to-terminal service (see “Write to terminal service” on page 430)
 Each service is described below.
9. The return code provided by the HLASM Services Interface service, indicating the status of the request. The values of the return code are:
 

0	Service completed successfully
4	Service-dependent value
8	Service-dependent value
20	Bad or unsupported service request type
24	Wrong number of arguments for this service type
28	Invalid argument for this service type
32	Returned-values list not long enough for this service type
10. The remaining words in the list are the argument words (set by the service requester) and the returned-value words (set by the HLASM Services Interface).

## Invoking the HLASM Services Interface

Use the following steps to invoke a service:

1. General Purpose Register 1 must point to the HLASM Services Interface block.
2. Set the service request type, the number of argument words, and the argument words in the HLASM Services Interface block, as described for the service you are requesting.
3. General Purpose Register 15 is the entry point to all HLASM Services Interface services. Its address is placed in the HLASM Services Interface block by HLASM. The AMODE (high order) bit set on the service entry-point address in the HLASM Services Interface Block.
4. General Purpose Register 14 contains the return address to the service requester. The assembler resets the caller’s AMODE mode back to what was provided at entry.
5. All registers are restored by HLASM on return.

The supported services and their service-interface descriptions are shown below.

## Get storage service

Table 39. Request to get storage

Field	Contents						
Request type	1 (get storage)						
Number of argument words: 2	<b>Word 1</b> Requested storage length <b>Word 2</b> Requested storage location: <table border="0"> <tr><td>1</td><td>Below 16MB line</td></tr> <tr><td>2</td><td>Below or above 16MB line</td></tr> <tr><td>3</td><td>Above 16MB line</td></tr> </table>	1	Below 16MB line	2	Below or above 16MB line	3	Above 16MB line
1	Below 16MB line						
2	Below or above 16MB line						
3	Above 16MB line						

Table 39. Request to get storage (continued)

Field	Contents
Number of returned-value words: 1	Word 1: Starting address of obtained storage
Return code	0 Request satisfied 4 Storage not available 8 Invalid argument 1 or 2

## Return storage service

Table 40. Request to return storage

Field	Contents
Request type	2 (return storage)
Number of argument words: 2	<b>Word 1</b> Returned storage length <b>Word 2</b> Returned storage starting address
Number of returned-value words: 0	
Return code	0 Request satisfied 4 Request failed

## Time and date service

Table 41. Request for time and date

Field	Contents
Request type	3 (time and date)
Number of argument words: 1	<b>Word 1</b> Result type 1 TIME DEC format
Number of returned-value words	2 <b>Word 1</b> time in unsigned packed decimal <b>Word 2</b> date in signed packed decimal
Return code	0 Request satisfied 4 Request failed

## Write to terminal service

Table 42. Request for time and date

Field	Contents
Request type	4 (write to terminal)
Number of argument words: 1	<b>Word 1</b> Address of the 2-byte message length, followed by a message string of at most 120 characters. <b>Word 2</b> Target of the message 1 Write to terminal 2 Write to SYSTERM data set if available, to terminal otherwise
Number of returned-value words: 0	

*Table 42. Request for time and date (continued)*

Field	Contents
Return code	0 Request satisfied
	4 Request failed

## Mapping the communication and work areas

The I/O exit and service-request parameter lists are mapped by DSECTs generated by the ASMAXITP macro, which is supplied by High Level Assembler with the macros used for installing and customizing the assembler.



---

## Appendix P. High Level Assembler for Linux on zSeries

This appendix provides information relevant to the Linux on zSeries implementation of High Level Assembler.

For information about system requirements, machine requirements, and storage requirements, see “Planning for installing High Level Assembler on zLinux” in the *HLASM Installation and Customization Guide*.

For installation details, see “Installing High Level Assembler on zLinux” in the *HLASM Installation and Customization Guide*.

For information about starting the assembler, see “Starting High Level Assembler on zLinux” in the *HLASM Installation and Customization Guide*.

For usage notes and limitations, see “Usage and limitations of High Level Assembler on zLinux” in the *HLASM Installation and Customization Guide*.

---

### Options

There are some differences between the options available for the assembler on Linux and other versions of assembler.

#### Sources of assembler options

- The ASMAOPT file is not available.
- The default options module is not available, so any reference to installation default options do not apply to the Linux assembler.

For more information, see Chapter 3, “Controlling your assembly with options,” on page 39.

#### Assembler options

There are options that are either not available, unique, or different for the Linux assembler.

##### **NOADATA**

Is the default for the ADATA option. The SYSADATA file is not available, so do not change this option.

**EXIT** This is not available to users on Linux (see ELF32 below).

##### **NODECK**

Default. Do not change.

##### **OBJECT**

This is the default. If you specify NOOBJECT then no object file will be written to the object path.

##### **NOGOFF**

If you are using ELF32 (see below) then do not change.

**SIZE** The default value is 32MB.

**ELF32** Linux only option.

The interface module will elide the ELF32 option and replace it with EX(OBX(ASMAXT2E)) and add the OBJ option if it is not already present. See “ELF32 option” for more details.

Chapter 4, “Providing user exits,” on page 87 is not applicable. No user exits are generally available.

Chapter 5, “Providing external functions,” on page 145 is not applicable. No external functions are available.

---

## ELF32 option

This is a Linux only option. It is provided to allow creation of ELF32 files directly.

If the ELF32 option is specified, then changes are made to the options passed to the assembler to invoke the exit.

The following considerations apply to generated ELF32 files:

1. All section lengths are rounded up to a doubleword.
2. ELF32 name lengths are set to the section length for SD, CM, and PC items, and to 4 for LD items. The name of the section is not affected.
3. Zero-length sections are assigned length 8.
4. RSects are assigned to ELF32 section `'.text.RSECT'`, and are assigned the executable attribute.
5. CSects are assigned to ELF32 section `'.data.CSECT'`, and are also assigned the data and executable attributes.
6. Common (CM) sections are assigned ELF32 section names `'.bss.<name>'`, where `<name>` is the name of the CM section.
7. High Level Assembler for Linux on zSeries converts only OBJ object files to ELF32 format.
8. When generating ELF32 object files, the following limitations apply:
  - a. A minimum of 25K working storage must be available
  - b. The GOFF option must not be specified.
  - c. Do not specify external names starting with an underscore (`_`), as they may conflict with Linux-generated names during the linking and loading process.
  - d. No entry points (LD items) may be specified in common sections.
  - e. Q-type and CXD-type address constants are not supported.
  - f. External dummy sections (DXD items, and dummy control sections referenced in Q-type address constants) are not supported.
  - g. Address constants of lengths other than 4 are not supported.
  - h. Only AMODE(31) and RMODE(ANY) are supported.
  - i. The following internal tables are currently limited to:
    - 50 control section (SD, CM, PC) names
    - 150 external symbols (SD, CM, PC, ER, WX)
    - 100 entry point (LD) names
    - 150 address constant items (RLD) residing in RSects
    - 150 address constant items (RLD) residing in CSects
    - 50 ELF32 string-table items
    - 100 ELF32 sections
    - 250 ELF32 symbols (including ELF32 section names)These limits are easily increased by recompiling ASMAXT2E.
  - j. Double relocations, although correctly converted, will not work, because the Linux `ld` command does not add the previous contents of an `adcon` field when performing relocations.

- k. Zero-length Private Code (PC) sections are ignored.
- l. Negative relocations (for example, A(0-\*)) are not supported.

---

## ASMAXT2E messages

ASMAXT2E may generate the following messages. Each message is prefixed with an assembler indication of the form ASMA70ns, where n is 0, 1, 2, 3, or 4, and s is one of the standard severity-indication letters I, W, E, S, T. This indication is followed by the word "OBJECT: ". Then, the message text is preceded by "ASMAXT2E: ".

---

### Exit not coded at same level (2,3) as Assembler

**Severity:** 16

**Explanation:** The ASMAXT2E module expects a different I/O exit interface from that supplied by High Level Assembler.

**User response:** This is an internal error. Report the problem to IBM service.

**System action:** Processing is terminated.

---

### Exit called for other than PUNCH or OBJECT

**Severity:** 16

**Explanation:** The ASMAXT2E module was invoked as an exit of type other than PUNCH or OBJECT.

**User response:** This is caused by incorrect assembler invocation options. Correct the options string and re-assemble.

**System action:** Processing is terminated.

---

### Exit not initialized, and not entered for OPEN

**Severity:** 16

**Explanation:** The ASMAXT2E module was expected to be open and initialized, but was not

**User response:** This is an internal error. Report the problem to IBM service.

**System action:** Processing is terminated.

---

### Insufficient working storage for exit

**Severity:** 16

**Explanation:** The ASMAXT2E module requires more working storage than is available.

**User response:** Specify a larger storage area, or specify a smaller SIZE option.

**System action:** Processing is terminated.

---

### Invalid action or operation type requested

**Severity:** 16

**Explanation:** The ASMAXT2E module was invoked as an I/O exit with an invalid action or operation type.

**User response:** This is an internal error. Report the problem to IBM service.

**System action:** Processing is terminated.

---

### Expecting input record, zero buffer length

**Severity:** 16

**Explanation:** The ASMAXT2E module expected to receive an object file record to process, but none was present.

**User response:** This is an internal error. Report the problem to IBM service.

**System action:** Processing is terminated.

---

### Close request for wrong exit type

**Severity:** 16

**Explanation:** The ASMAXT2E module received a CLOSE request, but for the wrong exit type.

**User response:** This is an internal error. Report the problem to IBM service.

**System action:** Processing is terminated.

---

### Invalid request-list options value

**Severity:** 12

**Explanation:** The ASMAXT2E module was invoked to process a record, but an options string was provided.

**User response:** This is an internal error. Report the problem to IBM service.

**System action:** Processing is terminated.

---

### Invalid parm-string length

**Severity:** 12

**Explanation:** The ASMAXT2E module was provided with a parameter string, but its length was invalid.

**User response:** Check that the assembler options specifying the I/O exit are valid.

## ASMAXT2E messages

**System action:** Processing is terminated.

---

### Too many ESD IDs

**Severity:** 12

**Explanation:** The program being processed has too many ESD items with distinct ESD IDs.

**User response:** Restructure the program to reduce the number of independently relocatable items.

**System action:** Processing is terminated.

---

### Too many RLD items

**Severity:** 12

**Explanation:** The program being processed has too many relocatable address constants.

**User response:** Restructure the program to reduce the number of address constants.

**System action:** Processing is terminated.

---

### Too many OBJ SD/CM/PC sections

**Severity:** 12

**Explanation:** The program being processed has too many control sections.

**User response:** Restructure the program to reduce the number of control sections.

**System action:** Processing is terminated.

---

### Too many ELF sections

**Severity:** 12

**Explanation:** The program being processed requires more ELF sections than can be provided.

**User response:** Restructure the program to reduce the number of independent items, or contact IBM service to request that ASMAXT2E be enhanced.

**System action:** Processing is terminated.

---

### String table overflow

**Severity:** 12

**Explanation:** The program being processed requires more space in the ELF string table than can be provided.

**User response:** Restructure the program to reduce the number of or length of external names, or contact IBM service to request that ASMAXT2E be enhanced.

**System action:** Processing is terminated.

---

### Too many LD items

**Severity:** 12

**Explanation:** The program being processed contains too many ENTRY names.

**User response:** Restructure the program to reduce the number ENTRY statements, or contact IBM service to request that ASMAXT2E be enhanced.

**System action:** Processing is terminated.

---

### Too many ELF symbols

**Severity:** 12

**Explanation:** The program being processed requires more ELF symbols than can be processed.

**User response:** Restructure the program to reduce the number of names, or contact IBM service to request that ASMAXT2E be enhanced.

**System action:** Processing is terminated.

---

### Insufficient storage for OBJ TXT records

**Severity:** 12

**Explanation:** The program being processed requires more work space than is available to process machine language instructions and data.

**User response:** Specify a larger storage area, or specify a smaller SIZE option.

**System action:** Processing is terminated.

---

### AMODE/RMODE 24 or 64 not supported in section 'xxxxxxx'

**Severity:** 8

**Explanation:** The program being processed contains a control section xxxxxxxx with an unsupported AMODE or RMODE.

**User response:** Modify the program to specify valid AMODE and RMODE.

**System action:** The section is discarded, and processing continues. No ELF object file will be produced.

---

### External Dummy (XD) item 'xxxxxxx' not supported

**Severity:** 8

**Explanation:** The program being processed contains a dummy external control section (XD) xxxxxxxx.

**User response:** Modify the program to remove the XD item.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.



---

**Adcon at xxxxxxxx in section with ID xxxx not 4 bytes long**

**Severity:** 8

**Explanation:** The program being processed contains an address constant at address xxxxxxxx in a control section with ESDID xxxx that is not 4 bytes long.

**User response:** Modify the program to correct the address constant.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**Adcon at xxxxxxxx in section with ID xxxx not type A or V**

**Severity:** 8

**Explanation:** The program being processed contains an address constant at address xxxxxxxx in a control section with ESDID xxxx of type Q, or DXD, or CXD.

**User response:** Modify the program to remove the address constant.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**Adcon at xxxxxxxx in section with ID xxxx requires unsupported negative relocation**

**Severity:** 8

**Explanation:** The program being processed contains an address constant at address xxxxxxxx in a control section with ESDID xxxx which requires negative relocation.

**User response:** Modify the program to remove the address constant.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**ELF file not produced due to previous errors**

**Severity:** 8

**Explanation:** Previous errors have suppressed the production of an ELF object file.

**User response:** Correct the errors.

---

**Section length on END record not supported**

**Severity:** 8

**Explanation:** The OBJ END record contains the length of a control section.

**User response:** The object file may be very old, possibly produced by a language translator that put the section length on the OBJ END record. (This condition will not arise with object files produced by High Level Assembler.)

---

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**Invalid END-record entry point request**

**Severity:** 8

**Explanation:** The OBJ END record contains a request for a particular entry point in the program.

**User response:** Remove the entry point request from the END record.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**LD item 'xxxxxxx' in unsupported section is ignored**

**Severity:** 8

**Explanation:** The ENTRY name xxxxxxxx is in a control section that was previously discarded.

**User response:** Correct the original error causing the section to be rejected.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**RLD item at address 'xxxxxxx' in unsupported section with ID 'xxxx' is ignored**

**Severity:** 8

**Explanation:** The RLD item at address xxxxxxxx in a control section with ESDID xxxx is in a control section that was previously discarded.

**User response:** Correct the original error causing the section to be rejected.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**RLD item at address 'xxxxxxx' in unsupported section with ID 'xxxx' references unsupported section**

**Severity:** 8

**Explanation:** The RLD item at address xxxxxxxx in a control section with ESDID xxxx references a position in a control section that was previously discarded.

**User response:** Correct the original error causing the section to be rejected.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

**Section 'xxxxxxx' ignored, addresses exceed X'FFFFFF'**

**Severity:** 8

**Explanation:** The control section named xxxxxxxx contains addresses either very close to or exceeding X'FFFFFF'.

---

## ASMAXT2E messages

**User response:** Reduce the size of the section, change its starting address, or (if the source program contains multiple control sections) re-assemble with the NOTHREAD option.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

### RLD items at 'xxxxxxx' in section with ID 'xxxx' cause double relocation

**Severity:** 8

**Explanation:** The RLD items at address xxxxxxxx in a control section with ESDID xxxx require more than a single relocation at that address.

**User response:** Change the program so that only a single relocation is required at a given address.

**System action:** The items are discarded, and processing continues. No ELF object file will be produced.

---

### No TXT records in OBJ file

**Severity:** 8

**Explanation:** The program generates no machine language instructions or data.

**User response:** Verify that the program is correctly coded. (A DSECT statement may be misplaced.)

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

### Entry point in zero-length PC section rejected

**Severity:** 8

**Explanation:** An entry point was specified in a zero-length Private Code section.

**User response:** Verify that the program is correctly coded.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

### LD item 'xxxxxxx' in section with ID 'xxxx' lies outside its owning section

**Severity:** 8

**Explanation:** An entry point named xxxxxxxx was specified that lies outside the bounds of its owning control section with ESDID xxxx.

**User response:** Verify that the program is correctly coded.

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

### LD item 'xxxxxxx' in COM section with ID 'xxxx' not supported

**Severity:** 8

**Explanation:** An entry point named xxxxxxxx was specified in a common (COM) control section with ESDID xxxx.

**User response:** Correct the program to remove the ENTRY point. (ENTRY points in COM sections are not supported; you may be able to reference items not at the origin of a COM section by specifying a constant offset in a referencing address constant.)

**System action:** The item is discarded, and processing continues. No ELF object file will be produced.

---

### Invalid or duplicate parm-string character ignored

**Severity:** 0

**Explanation:** An invalid or duplicated character appears in the parameter string provided to ASMAXT2E.

**User response:** Correct the options invoking ASMAXT2E to specify valid characters.

**System action:** The item is ignored, and processing continues.

---

### nnnnnnnnn SYM records ignored

**Severity:** 0

**Explanation:** The OBJ file contained nnnnnnnnn SYM records, produced when the TEST option is provided to High Level Assembler.

**User response:** Correct the options invoking High Level Assembler.

**System action:** The records are ignored, and processing continues.

---

### nnnnnnnnn non-OBJect record(s) ignored

**Severity:** 0

**Explanation:** The OBJ file contained nnnnnnnnn records that are not object-module records.

**User response:** The program may contain PUNCH or REPRO statements. Verify that they are not required.

**System action:** The records are ignored, and processing continues.

---

### Zero-length Private Code (PC) section ignored

**Severity:** 0

**Explanation:** The program contains a zero-length Private Code (PC) section.

**User response:** Correct the source program.

**System action:** The section is ignored, and processing continues.

---

xxxxxxx object records processed, xxxx usable control section(s)

**Severity:** 0

**Explanation:** The program produced xxxxxxxx object records, and xxxx control sections were converted to ELF format.

---

ELF file length X'xxxxxxx'

**Severity:** 0

**Explanation:** The generated ELF file is X'xxxxxxx' bytes long.

## ASMAXT2E messages

---

## Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Mail Station P300  
2455 South Road  
Poughkeepsie New York 12601-5400  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR

## Notices

PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

---

## Trademarks

The following are trademarks of International Business Machines Corporation in the United States, or other countries, or both.

AIX  
BookMaster  
DFSMS  
DFSMS/MVS  
DFSMSdfp  
Enterprise System/9000  
Enterprise Systems Architecture/370  
Enterprise Systems Architecture/390  
ES/9000  
ESA/390  
IBM  
MVS  
MVS/DFP  
MVS/ESA  
OS/390  
S/370  
SP  
System/370  
System/390  
VSE/ESA  
3090  
z/VM  
z/OS  
z/OS Unix Services  
z/VM  
z/VSE  
zSeries

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Microsoft and Windows are trademarks of Microsoft Corporation in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.





---

## Glossary

This glossary defines terms that are used in the High Level Assembler publications. Some of these terms might not be used in this publication.

This glossary has three main types of definitions that apply:

- To the assembler language in particular (usually distinguished by reference to the words “assembler,” “assembly,” etc.)
- To programming in general
- To data processing as a whole

If you do not understand the meaning of a data processing term used in any of the definitions below, refer to *Vocabulary for Data Processing, Telecommunications, and Office Systems*, GC20-1699.

IBM is grateful to the American National Standards Institute (ANSI) for permission to reprint its definitions from the American National Standard Vocabulary for Information Processing, which was prepared by Subcommittee X3K5 on Terminology and Glossary of American National Standards Committee X3. ANSI definitions are preceded by an asterisk (\*).

**absolute expression.** An expression is absolute if its value does not change upon program relocation.

**absolute value.** Is the value of a term when that value does not change upon program relocation.

**ADATA.** (See **associated data**.) An assembler option causing it to produce associated data.

**addressing mode (24-bit).** A System/370 addressing mode (AMODE) of the extended architecture that allows a program to run using 24-bit addresses. When operating in 24-bit mode, S/370™ addressing architecture is applied. Other facilities of the extended architecture (see below) may be utilized. Only the low-order 24 bits of an address are used; the high-order bits are ignored.

**addressing mode (31-bit).** An extended architecture addressing mode (AMODE) that allows a program to run using 31-bit addresses, other facilities of the extended architecture, or both. When operating in 31-bit mode, extended architecture addressing is applied, and all but the high-order bit of an address are used to address storage.

**assemble.** To prepare a machine language program from a symbolic language program by substituting

machine operation codes for symbolic operation codes and absolute or relocatable addresses for symbolic addresses.

**\*assembler.** A computer program that assembles.

**assembler instruction.** An assembler language source statement that causes the assembler to do a specific operation. Assembler instructions are not translated into machine instructions.

**assembler language.** A source language that includes symbolic machine language statements in which there is a one-to-one correspondence with the instruction formats and data formats of the computer. The assembler language also contains statements that represent assembler instructions and macro instructions.

**associated data.** Additional information produced by the assembler containing detailed machine-readable information about the assembly.

**automatic library call.** The process by which the linkage editor or binder resolves external references by including additional members from the automatic call library.

**bimodal program execution.** A function of the extended architecture (see “addressing mode (31-bit)”) that allows a program to run in 24-bit or 31-bit addressing mode. The addressing mode is under program control.

**binder.** The component of DFSMS/MVS which is responsible for linking and editing programs, to create either record format load modules or program objects. The z/OS binder is a functional replacement for the z/OS linkage editor.

**bracketed DBCS.** DBCS characters enclosed with a shift-out (SO) character and a shift-in character (SI) to identify them from SBCS, and containing no SBCS characters except SO and SI.

**class.** A cross-section of program object data with uniform format, content, function, and behavioral attributes.

**code page.** An assignment of graphic characters and control function meanings to all code points.

**code point.** A 1-byte code representing one of 256 potential characters.

**COMMON.** A control section having a length attribute but no machine language text, for which space is reserved in the executable program.

**conditional assembly language.** A programming language that the assembler processes during conditional assembly. The conditional assembly language can be used to perform general arithmetic and logical computations, generate machine and assembler instructions from model statements, and provide variable symbols to represent data and vary the content of model statements during generation. It can be used in macro definitions, and in open code.

**CONTROL PROGRAM..** A program that is designed to schedule and supervise the performance of data processing work by a computing system; an operating system.

**control section (CSECT).** That part of a program specified by the programmer to be a relocatable unit, all elements of which are to be loaded into adjoining main storage locations.

**data attributes.** Values assigned by the assembler which describe the characteristics of ordinary symbols and variable symbols that represent data.

**\*diagnostic.** Pertaining to the detection and isolation of a malfunction or mistake.

**double-byte character set (DBCS).** DBCS is a means of providing support for Ideographic Languages which contain too many symbols to be represented by a single byte character set such as EBCDIC. A valid double-byte character is defined as either DBCS space (X'4040'), or a pair of bytes, each of which must be in the range X'41' to X'FE', inclusive.

**double-byte data.** Double-byte character strings are commonly referred to as double-byte data.

**dummy control section (DSECT).** A control section that an assembler can use to map an area of storage without producing any object code or data for that area. Synonymous with dummy section.

**edited text.** Source statements modified by the assembler for internal use. The initial processing of the assembler is referred to as editing.

**element.** The unit of program object data uniquely identified by a section name and a class name.

**enterprise systems architecture.** A hardware architecture for the IBM 3090 processor. A major characteristic is 31-bit addressing. See also "addressing mode (31-bit)".

**\*entry point.** A location in a module to which control can be passed from another module or from the control program.

**extended architecture.** A hardware architecture for systems beginning with the IBM 3081. A major characteristic is 31-bit addressing. See also "addressing mode (31-bit)".

**external symbol dictionary (ESD).** Control information associated with an object or load module which identifies the external symbols in the module.

**global dictionary.** An internal table used by the assembler during macro generation to contain the current values of all unique global SETA, SETB, and SETC variables from all text segments.

**global vector table.** A table of pointers in the skeleton dictionary of each text segment showing where the global variables are located in the global dictionary.

**GOFF.** Generalized Object File Format.

**hierarchical file system.** In z/OS UNIX System Services, a Hierarchical File System (HFS) is a collection of files organized in a hierarchy, as in a UNIX system. All files are members of a directory, and each directory is in turn a member of another directory at a higher level in the hierarchy. The highest level of the hierarchy is the root directory. z/OS views an entire file hierarchy as a collection of hierarchical file system data sets (HFS data sets). Each HFS data set is a mountable file system. The Hierarchical File System is described in the *z/OS UNIX System Services User's Guide*.

**instruction.** \*(1) A statement that specifies an operation and the values and locations of its operands. (2) See also "assembler instruction", "machine instruction", and "macro instruction".

**job control language (JCL).** A language used to code job control statements.

**\*job control statement.** A statement in a job that is used in identifying the job or describing its requirements to the operating system.

**language.** A set of representations, conventions, and rules used to convey information.

**\*language translator.** A general term for any assembler, compiler, or other routine that accepts statements in one language and produces equivalent statements in another language.

**library macro definition.** A macro definition that is stored in a macro library. The IBM-supplied supervisor and data management macro definitions are examples of library macro definitions.

**linkage editor.** A processing program that prepares the output of language translators to enable it to run. It combines separately produced object or load modules; resolves symbolic cross references among them; replaces, deletes, and adds control sections; generates overlay structures on request; and produces executable code (a load module) that is ready to be fetched into main storage and run.

**linker.** Used in this publication as collective term for *binder* and *linkage editor*.

**load module.** The output of a single linkage editor run. A load module is in a format suitable for loading into virtual storage and running.

**loader.** A processing program that does the basic editing functions of the linkage editor, and also fetches and gives control to the processed program. It accepts object modules and load modules created by the linkage editor and generates executable code directly in storage. The loader does not produce load modules for program libraries.

**local dictionary.** An internal table used by the assembler during macro generation to contain the current values of all local SET symbols. There is one local dictionary for open code, and one for each macro definition.

**location counter.** A counter whose value indicates the assembled address of a machine instruction or a constant or the address of an area of reserved storage, relative to the beginning of the control section.

**\*machine instruction.** An instruction that a machine can recognize and execute.

**\*machine language.** A language that is used directly by the machine.

**macro definition.** A set of statements that defines the name of, format of, and conditions for generating a sequence of assembler language statements from a single source statement. This statement is a macro instruction that calls the definition. (See also "library macro definition" and "source macro definition".)

**macro generation (macro expansion).** An operation in which the assembler generates a sequence of assembler language statements from a single macro instruction, under conditions described by a macro definition.

**macro instruction (macro call).** An assembler language statement that causes the assembler to process a predefined set of statements (called a macro definition). The statements normally produced from the macro definition replace the macro instruction in the source program.

**macro library.** A library containing macro definitions. The supervisor and data management macro definitions supplied by IBM (GET, LINK, etc.) are contained in the system macro library. Private macro libraries can be concatenated with the system macro library.

**macro prototype statement.** An assembler language statement that specifies the mnemonic operation code and the format of all macro instructions that are used to call a macro definition.

**MACRO statement.** An assembler language statement that indicates the beginning of a macro definition. (Also known as a macro definition header).

**main storage.** All program addressable storage from which instructions may be executed and from which data can be loaded directly into registers.

**MEND statement.** An assembler language statement that indicates the end of a macro definition. (Also known as a macro definition trailer).

**model statement.** A statement from which assembler language statements are generated during conditional assembly.

**object module.** The machine-language output of a single run of an assembler or a compiler. An object module is used as input to the linkage editor, loader, or binder.

**open code.** The portion of a source module that lies outside of and after any source macro definitions that may be specified.

**\*operating system.** Software that controls the running of computer programs and which may provide scheduling, debugging, input/output control, accounting, compilation, storage assignment, data management, and related services. (see "control program".)

**ordinary symbol attribute reference dictionary.** A dictionary used by the assembler. The assembler puts an entry in it for each ordinary symbol encountered in the name field of a statement. The entry contains the attributes (type, length, etc.) of the symbol.

**Part Reference.** A named subdivision of a MERGE class in a program object. A Pseudo-Register (external dummy section) or an external data item, having length and alignment attributes. Space in the loaded program is reserved for Parts (which may contain machine language text), but not for Commons or Pseudo-Registers.

**partitioned data set (PDS).** A data set on direct access storage that is divided into partitions, called members, each of which can contain a program, part of a program, or data.

**PDSE (partitioned data set extended).** A system-managed data set that contains an indexed directory and members that are similar to the directory and members of partitioned data sets.

**phase.** The output of a single z/VSE linkage editor run. A phase is in a format suitable for loading into virtual storage

**processing program.** (1) A general term for any program that is not a control program. (2) Any program capable of operating in the problem program state. This includes IBM-distributed language translators, application programs, service programs, and user-written programs.

**program.** A general term for any combination of statements that can be interpreted by a computer or language translator, and that serves to do a specific function.

**program fetch.** A program that prepares programs for execution by loading them at specific storage locations and readjusting each (relocatable) address constant.

**program library.** A partitioned data set or PDSE (z/OS), or Librarian library (z/VSE), that always contains named members.

**program management binder.** See *binder*.

**program module.** Used in this publication as collective term for *load module* and *program object*.

**program object.** A new form of executable program supporting one or more independently relocatable loadable segments. Program objects are stored in PDSE program libraries, and are produced by the Program Management Binder.

**pure DBCS.** DBCS characters not delimited by SO and SI. These characters must be known to be DBCS by some other method, such as the position in a record, or a field type descriptor in a database environment.

**real storage.** The storage of a System/370 computer from which the central processing unit can directly obtain instructions and data, and to which it can directly return results.

**read-only control section (RSECT).** That part of a program specified by the programmer to be a read-only executable control section. The assembler automatically checks the control section for possible coding violations of program reenterability, regardless of the setting of the RENT assembler option.

**reenterable.** An attribute that allows a program to be used concurrently by more than one task. This attribute is sometimes called *reentrant*.

**refreshable.** An attribute that allows a program to be replaced with a new copy without affecting its operation.

**reusability.** An attribute of a program that defines the scope to which it can be reused or shared by multiple tasks within an address space.

**relocatable expression.** An expression is relocatable if its value changes because the control section in which it appears is relocated.

**relocatable value.** Is the value of a term when that value changes because the control section in which it appears is relocated.

**\*relocation dictionary.** The part of an object or load module that identifies all addresses that must be adjusted when a relocation occurs.

**residence mode.** An extended architecture addressing mode (RMODE) that allows a program to specify the residence mode (below 16 megabytes or anywhere) to be associated with a control section.

**return code.** A value placed in the return code register at the completion of a program. The value is established by the user and may be used to influence the running of succeeding programs or, in the case of an abnormal end of task, may simply be printed for programmer analysis.

**section.** (1) A cross-section of program object data with a single name, consisting of elements belonging to one or more classes. (2) A control section.

**segment.** The aggregate of all section contributions to a given class, loaded as a single entity into storage, and having its own relocation base address.

**severity code.** A code assigned by the assembler to each error detected in the source code. The highest code encountered during assembly becomes the return code of the assembly step.

**shift-in (SI).** The shift-in (SI) EBCDIC character (X'0F') delimits the end of double-byte data.

**shift-out (SO).** The shift-out (SO) EBCDIC character (X'0E') delimits the start of double-byte data.

**skeleton dictionary.** A dictionary built by the assembler for each text segment. It contains the global vector table, the sequence symbol reference dictionary, and the local dictionary.

**source macro definition.** A macro definition included in a source module, either physically or as the result of a COPY instruction.

**source module.** The source statements that constitute the input to a language translator for a particular translation.

**source statement.** A statement written in a programming language.

**\*statement.** A meaningful expression or generalized instruction in a programming language.

**symbol file.** A data set used by the assembler for symbol definitions and references and literals.

**symbolic parameter.** In assembler programming, a variable symbol declared in the prototype statement of a macro definition.

**system macro definition.** Loosely, an IBM-supplied library macro definition which provides access to operating system facilities.

**text.** Machine language instructions and data.

**text segment.** The range over which a local dictionary has meaning. The source module is divided into text segments with a segment for open code and one for each macro definition.

**\*translate.** To transform statements from one language into another without significantly changing the meaning.

**trimodal program execution.** A function of z/Architecture that allows a program to run in 24-bit, 31-bit, or 64-bit address mode. The addressing mode is under program control.

**translate table.** A table used to replace one or more characters with alternative characters.

**virtual storage.** Address space appearing to the user as real storage from which instructions and data are mapped into real storage locations. The size of virtual storage is limited by the addressing scheme of the computing system and by the amount of auxiliary storage available, rather than by the actual number of real storage locations.

**ward.** A set of DBCS characters which have the same high-order byte value. The first byte of a double-byte character is known as the ward byte. A ward contains 190 characters. Ward X'42' defines the double-byte representation of those EBCDIC characters which are in the range X'41' to X'FE'.





---

## Bibliography

---

### High Level Assembler Publications

*HLASM General Information*, GC26-4943  
*HLASM Installation and Customization Guide*, SC26-3494  
*HLASM Language Reference*, SC26-4940  
*HLASM Licensed Program Specifications*, GC26-4944  
*HLASM Programmer's Guide*, SC26-4941

---

### Toolkit Feature Publications

*HLASM Toolkit Feature User's Guide*, GC26-8710  
*HLASM Toolkit Feature Debug Reference Summary*, GC26-8712  
*HLASM Toolkit Feature Interactive Debug Facility User's Guide*, GC26-8709  
*HLASM Toolkit Feature Installation and Customization Guide*, GC26-8711

---

### Related Publications (Architecture)

*Enterprise Systems Architecture/390 Principles of Operation*, SA22-7201  
*Enterprise Systems Architecture/370 Principles of Operation*, SA22-7200  
*System/370 Principles of Operation*, GA22-7000  
*System/370 Extended Architecture Principles of Operation*, SA22-7085  
*z/Architecture Principles of Operation*, SA22-7832

---

### Related Publications for z/OS

**z/OS:**  
*z/OS MVS JCL Reference*, SA22-7597  
*z/OS MVS JCL User's Guide*, SA22-7598  
*z/OS MVS Programming: Assembler Services Guide*, SA22-7605  
*z/OS MVS Programming: Assembler Services Reference, Volumes 1 and 2*, SA22-7606, SA22-7607  
*z/OS MVS Programming: Authorized Assembler Services Guide*, SA22-7608

*z/OS MVS Programming: Authorized Assembler Services Reference, Volumes 1 - 4*, SA22-7609 - SA22-7612

*z/OS MVS Program Management: User's Guide and Reference*, SA22-7643

*z/OS MVS System Codes*, SA22-7626

*z/OS MVS System Commands*, SA22-7627

*z/OS MVS System Messages, Volumes 1 - 10*, SA22-7631 - SA22-7640

*z/OS Communications Server: SNA Programming*, SC31-8829

#### **OS/390:**

*OS/390 MVS System Messages, Volumes 1 - 5*, GC28-1784 - GC27-1788

#### **UNIX System Services:**

*z/OS UNIX System Services User's Guide*, SA22-7801

#### **DFSMS/MVS™:**

*z/OS DFSMS Program Management*, SC27-1130

*z/OS DFSMSdfp Utilities*, SC26-7414

#### **TSO/E (z/OS):**

*z/OS TSO/E Command Reference*, SA22-7782

#### **TSO/E (OS/390):**

*OS/390 TSO/E Command Reference*, SC28-1969

#### **SMP/E (z/OS):**

*SMP/E Messages, Codes, and Diagnosis*, GA22-7770

*SMP/E Reference*, SA22-7772

*SMP/E User's Guide*, SA22-7773

#### **SMP/E (OS/390):**

*OS/390 SMP/E Messages and Codes*, SC28-1738

*OS/390 SMP/E Reference*, SC28-1806

*OS/390 SMP/E User's Guide*, SC28-1740

---

### Related Publications for z/VM

*z/VM: VMSES/E Introduction and Reference*, GC24-6130

*z/VM: Service Guide*, GC24-6117

*z/VM: CMS Commands and Utilities Reference*, SC24-6073

*z/VM: CMS File Pool Planning, Administration, and Operation*, SC24-6074

*z/VM: CP Planning and Administration*,  
SC24-6083

*z/VM: Saved Segments Planning and  
Administration*, SC24-6116

*z/VM: Other Components Messages and Codes*,  
GC24-6120

*z/VM: CMS and REXX/VM Messages and Codes*,  
GC24-6118

*z/VM: CP System Messages and Codes*,  
GC24-6119

*z/VM: CMS Application Development Guide*,  
SC24-6070

*z/VM: CMS Application Development Guide for  
Assembler*, SC24-6070

*z/VM: CMS User's Guide*, SC24-6079

*z/VM: XEDIT User's Guide*, SC24-6132

*z/VM: XEDIT Commands and Macros Reference*,  
SC24-6132

*z/VM: CP Commands and Utilities Reference*,  
SC24-6081

---

## **Related Publications for z/VSE**

*z/VSE: Guide to System Functions*, SC33-8233

*z/VSE: Administration*, SC33-8224

*z/VSE: Installation*, SC33-8222

*z/VSE: Planning*, SC33-8221

*z/VSE: System Control Statements*, SC33-8225

*z/VSE: Messages and Codes, Vol.1*, SC33-8226

*z/VSE: Messages and Codes, Vol.2*, SC33-8227

*z/VSE: Messages and Codes, Vol.3*, SC33-8228

*REXX/VSE Reference*, SC33-6642

*REXX/VSE User's Guide*, SC33-6641



---

# Index

## Special characters

- \*PROCESS OVERRIDE assembler options 40
- \*PROCESS statements
  - OVERRIDE 41
  - precedence of assembler options 39
- &SYSNDX system variable symbol, controlling its value using MHELP 326

## Numerics

- 121-character format, source and object listing 14
- 121, LIST assembler suboption 61
- 133-character format, source and object listing 14
- 133, LIST assembler suboption 61
- 370, OPTABLE assembler suboption 66

## A

- abnormal assembly termination 156
- ABOVE, suboption of SIZE 74
- accessing the assembler (CMS) 199
- ACONTROL statement
  - COMPAT/NOCOMPAT option 47
  - FLAG option 54
  - LIBMAC/NOLIBMAC option 61
  - RA2/NORA2 option 71
  - TC/NOTC option 80
- active USINGs
  - in the assembler listing 19
  - UHEAD, PCONTROL assembler suboption 67
- ADATA
  - assembler option 43, 267
  - definition 445
  - exit processing 120
  - GOFF assembler suboption 57, 267
  - WORKFILE assembler suboption 83
  - XOBJECT assembler suboption 84
- adding macro definitions to libraries
  - CMS 213
  - z/OS 183
  - z/VSE 233
- addressing mode 180
- ADEXIT
  - EXIT assembler suboption 51
  - installation option 53
- ALIGN
  - assembler option 44, 224
  - FLAG assembler suboption 54
- ALIGNWARN installation option 57
- alternate ddnames 165
- AMODE
  - binder option 179
  - in ESD section of listing 14
  - processing option 180
- architecture level in ADATA records 274
- ASA assembler option 45
- ASA assembler option (CMS) 204
- ASA assembler option (z/OS) 169
- ASCII translation table 79
- ASMACH
  - cataloged procedure for assembly 162
- ASMACHG
  - cataloged procedure for assembly and run, using the loader 189
- ASMAHL
  - cataloged procedure for assembly and link 186
- ASMAHLG
  - cataloged procedure for assembly, link, and run 189
- ASMADATA macro 267, 389
- ASMAEFNP macro 146, 389
- ASMAHL command
  - by FILEDEF for SYSIN 204
  - error messages 385
  - with filename of source 204
  - with the EXIT option 205
- ASMAHL command-error messages 335
- ASMAOPT
  - data set 167, 170
  - macro 40
  - options file/library member 40
- ASMAPROF, default profile member name 70
- ASMATXT2E messages 435
- ASMAXADC (ADATA user exit) 397
- ASMAXADR (ADATA user exit) 399
- ASMAXADT (ADATA user exit) 391
- ASMAXFMB macro 389, 391
- ASMAXINV (SOURCE user exit) 405
- ASMAXITP macro 90, 389, 431
- ASMAXPRT (LISTING user exit) 403
- assembler
  - language differences 239
  - sample program 313
- assembler cataloged procedures
  - cataloged procedure for assembly 184
- assembler data sets (z/OS)
  - characteristics of 167
  - list of 166
- assembler diagnostics
  - abnormal assembly termination 156
  - cross reference 22
  - differences 254
  - error messages 153
  - facilities 153
  - macro trace facility (MHELP) 157
  - MNOTE statements 155
  - National Language Support 60
  - reference information for statements in error 156
  - register cross reference 32
  - suppression of error messages and MNOTE statements 156

- assembler files (CMS)
  - characteristics of 203
  - list of 202
- assembler files (z/VSE)
  - characteristics of 226
  - list of 225
- Assembler H Version 2 compatibility 4
- Assembler information block 99
- assembler language support 4
- assembler listing
  - \*PROCESS statements 8
  - 121-character format 14
  - 133-character format 14
  - CMS options that affect 8
  - diagnostic cross reference and assembler summary 33
  - differences 252
  - DSECT cross reference 30
  - external symbol dictionary 11
  - general purpose register cross reference 32
  - macro and copy code cross reference 26
  - macro and copy code source summary 25
  - option summary 8
  - options that affect 7
  - parts of 7
  - relocation dictionary 21
  - source and object 14, 15
  - source and object, 121 character format 15
  - source and object, 133 character format 20
  - symbol and literal cross reference 22
  - unreferenced symbols defined in CSECTs 25
  - USING map 30
- assembler macros
  - on CMS 213
  - on z/OS 183
- assembler option OBJECT 58
- assembler options
  - \*PROCESS OVERRIDE 40
  - \*PROCESS statements 41
  - See also* options
  - ADATA 43, 267
  - ALIGN 44, 224
  - ASA 45, 169, 204
  - ASMAOPT 40
  - at invocation 40
  - BATCH 45
  - CODEPAGE 46
  - coding rules 42
  - COMPAT 47
  - conflicting 39
  - DBCS 48
  - DECK 48, 224
  - default 42
  - differences 250

## assembler options (continued)

- DISK (CMS) 69
- DXREF 49
- ERASE (CMS) 49
- ESD 50
- EXIT 51, 88
- external source 40
- external sources 39
- fixed defaults 40
- FLAG 54
- FOLD 57
- GOFF 57
- in a parameter list 42
- INFO 59
- JCL options 224
- LANGUAGE 60
- LIBMAC 60
- LINECOUNT 61
- LIST 61, 224
- MACHINE 62
- MXREF 64
- NOADATA 43, 267
- NOALIGN 44, 224
- NOASA 45, 169, 204
- NOBATCH 45
- NOCOMPAT 47
- NODBCS 48
- NODECK 48, 224
- NODXREF 49
- NOERASE (CMS) 49
- NOESD 50
- NOEXIT 51
- NOFOLD 57
- NOGOFF 57
- NOINFO 59
- NOLIBMAC 60
- NOLIST 61, 224
- NOMXREF 64
- NOOBJECT 65, 224
- NOPCONTROL 67
- NOPRINT (CMS) 69
- NOPROFILE 70
- NORA2 71
- NORENT 71
- NORLD 72, 224
- NORXREF 72
- NOSEG 73
- NOSUPRWARN 76
- NOTERM 77, 224
- NOTEST 78
- NOTHREAD 78
- NOTRANSLATE 79
- NOTYPECHECK 79
- NOUSING 81
- NOWORKFILE 83
- NOXOBJECT 84
- NOXREF 84, 224
- OBJECT 65, 224
- on CMS 201
- OPTABLE 66
- override 40
- OVERWRITE on \*PROCESS statement 41
- overriding defaults 42, 190
- PCONTROL 67
- PESTOP 69
- precedence 39

## assembler options (continued)

- PRINT (CMS) 69
- processing 178
- PROFILE 70
- RA2 71
- RENT 71
- restricted options 41
- RLD 72, 224
- RXREF 72
- sample of use 315
- SECTALGN 73
- SEG 73
- SIZE 74
- source 39
- SUPRWARN 76
- SYSPARM 76
- TERM 77, 224
- TEST 78
- THREAD 78
- TRANSLATE 79
- TYPECHECK 79
- types of 39
- USING 81
- WORKFILE 83
- XOBJECT 84
- XREF 84, 224
- Assembler options
  - overriding 190
  - overriding statements in cataloged procedures 190
- assembler statistics 36
- assembler summary 33
- assembler type 22, 24
- assembling your program 219
- assembly abnormal-termination messages 335
- assembly error diagnostic messages 338
- assembly error-diagnostic messages 335
- associated data records
  - ADATA compilation unit start/end record - X'0002' 278
  - ADATA identification record - X'0001' 278
  - architecture level 267, 274
  - ASMA data macro 267
  - common header section 274
  - DC extension record - X'0035' 301
  - DC/DS record - X'0034' 294
  - external symbol dictionary record - X'0020' 290
  - job identification record - X'0000' 276
  - library member and macro cross reference record - X'0062' 306
  - library record - X'0060' 305
  - machine instruction record - X'0036' 301
  - options file information - X'000B' 283
  - options record - X'0010' 284
  - output file information record - X'000Aa' 279
  - register cross reference record - X'0045' 304
  - relocation dictionary record - X'0040' 301
  - source analysis record - X'0030' 291
  - statistics record - X'0090' 309

## associated data records (continued)

- symbol and literal cross reference record - X'0044' 303
- symbol record - X'0042' 302
- user-supplied information record - X'0070' 307
- USING map record - X'0080' 308
- associated data, definition 445
- ATTACH macro instruction, (z/OS) 164
- automatic call library
  - definition 445
  - secondary data set 176

## B

- BATCH assembler option 45
- batch assembling 223
  - CMS 201
  - z/OS 166
- batch facility on CMS 210
- binder
  - generalized object format 84
  - options (z/OS) 179
  - sample JCL 175
  - z/OS
    - input 176
    - primary 176
    - secondary 176
- BLKSIZE for assembler files 227
  - CMS 204
  - z/OS 169
- books, High Level Assembler xii

## C

- CALL binder option 179
- CALL macro instruction 222
- CALL macro instruction (z/OS) 164
- calling the assembler from a problem program 222
- calling the assembler from program (z/OS) 164
- CASE, COMPAT assembler suboption 47
- cataloged procedures
  - for assembling (ASMAC) 184
  - for assembling and linking (ASMACL) 186
  - for assembling and running using the loader (ASMACG) 189
  - for assembling, linking, and run (ASMACLG) 189
  - invoking 184
  - overriding 190
- CATTR instruction, interaction with GOFF 58
- CD-ROM publications xiii
- CDLOAD macro instruction 222
- characteristics of assembler data sets (z/OS) 167
- characteristics of assembler files (CMS) 203
- characteristics of assembler files (z/VSE) 226
- class, definition 445
- CLOSE calls to user exit 92

- CMS
  - ASMAHL command error
    - messages 385
  - assembler macros supported by 213
  - assembling on 200
  - batch facility 210
  - diagnostic messages 385
  - logical saved segments 73
  - relationship to assembler 199
  - running on 209
- CMS assembler options 201
- CMS diagnostic messages 207
- CMSBATCH command 210
- CODEPAGE assembler option 46
- coding rules for assembler options 42
- COM instruction
  - interaction with GOFF 58
- COMMON, definition 445
- COMPAT assembler option 47
- compatibility with earlier assemblers 4
- concatenation of sublibraries 227
- concatenation of SYSLIB data sets 170, 206
- COND parameter 171, 191
- conditional assembly external
  - functions 145
- CONT, FLAG assembler suboption 54
- CONTWARN installation option 57
- create, phase 229
- cross reference
  - binder (z/OS) 178
  - data variables (z/OS) 178
  - examples 7, 325
  - linkage editor 232
- cross reference list
  - DSECT 30
- CSECT instruction
  - interaction with GOFF 58
- Customization book xii

## D

- data
  - variables, cross reference 178
- data sets, assembler (z/OS)
  - characteristics of 167
  - list of 166
- DATA, PCONTROL assembler
  - suboption 67
- DBCS assembler option 48
- DD statements, overriding in cataloged
  - procedures 190
- ddnamelist 165
- ddnames
  - alternate 165
  - SYSADATA 171, 207
  - SYSIN 170, 205
  - SYSLIB 170, 177, 206
  - SYSLIN 171, 177, 207
  - SYSLMOD 177
  - SYSPRINT 170, 177, 206
  - SYSPUNCH 171, 207
  - SYSTEM 170, 177, 206
  - SYSUT1 177
  - user-specified 177
- DE, LANGUAGE assembler
  - suboption 60

- DECK assembler option 48, 224
- default options 42
- default profile member name 70
- diagnostic cross reference and assembler
  - summary 33
- diagnostic messages written by
  - CMS 207, 385
- diagnostic messages, assembly error 338
- DISK assembler option (CMS) 69
- documentation
  - High Level Assembler 451
- documentation, High Level
  - Assembler xii
- DOS, OPTABLE assembler suboption 66
- DOS/VSE assembler compatibility 4
- DSECT cross reference listing format 30
- DXREF assembler option 49
- dynamic invocation of assembler 222
- dynamic invocation of assembler
  - (z/OS) 164

## E

- E-Decks, processing 233
- element, definition 446
- ELF32 assembler option 433
- ELF32 object files
  - creating 434
- ELF32 option
  - implementation notes 434
- EN, LANGUAGE assembler
  - suboption 60
- END OF MEMBER calls to user exit 92
- END Record format 262
- entry point restatement 195
- ERASE assembler option (CMS) 49
- erasing files (CMS) 49
- error messages
  - abnormal assembly termination
    - messages 380
  - ASMAHL command error messages
    - (CMS) 385
  - assembly error diagnostic
    - messages 153, 338
  - reference information 156
  - suppression of 54, 156
- error, binder (z/OS) 181
- error, link-edit 232
- ES, LANGUAGE assembler
  - suboption 60
- ESA
  - OPTABLE assembler suboption 66
- ESD assembler option 50
- ESD Record format 259
- ESDID
  - in Ordinary Symbol and Literal Cross
    - Reference 24
  - in USING Map 31
- examples
  - cataloged procedures coding 191
  - register saving and restoring
    - coding 234
  - register saving and restoring coding
    - (CMS) 214
  - register saving and restoring coding
    - (z/OS) 193

- EXEC statements, overriding in cataloged
  - procedures 191
- EXIT assembler option 51, 88, 433
- EXIT option with the ASMAHL
  - command 205
- exit parameter list 90
- exit types 87
- exit-specific information block 101
- EXITCTL assembler instruction 88
- exits
  - user-supplied 87
- EXLITW, FLAG assembler suboption 54
- external functions 145, 434
- external symbol dictionary (ESD)
  - entry types 11
  - examples 12
  - listing format 11

## F

- FILEDEF with the ASMAHL
  - command 204
- filename with ASMAHL command 204
- files, assembler (CMS)
  - characteristics of 203
  - list of 202
- files, assembler (z/VSE)
  - characteristics of 226
  - list of 225
- files, linkage editor
  - SYSIPT 231
  - SYSLNK 231
  - SYSLOG 231
  - SYSLST 231
  - SYSRDR 231
- filter management table (ADATA user
  - exit) 391
- filter modules (ADATA user exit) 391
- FIND COPY calls to user exit 92
- FIND MACRO calls to user exit 92
- FLAG assembler option 54
- FOLD assembler option 57
- format notation, description xiii
- FULL
  - MXREF assembler suboption 64
  - XREF assembler suboption 84
- function calls, external 145

## G

- GEN, PCONTROL assembler
  - suboption 67
- General Information book xii
- general purpose register cross
  - reference 32
- generalized object format data set 84
- generate a translation table 407
- generate a Unicode translation table 409
- GENMOD command (CMS) 209
- GOFF
  - assembler option 57
  - definition 446
- graphic constants 48

## H

- hardcopy publications xii
- hierarchical file system
  - definition 446
  - object data sets 168
- High Level Assembler
  - publications xii
- High Level Assembler messages 335
- High Level Assembler option
  - summary 8
- HLASM Services Interface pointer 100

## I

- I/O Exit Usage Statistics
  - in the listing 36
- ICCF, assembling on 220
- identification-sequence field 17
- IF statement 228
- IJSYS01 230
- IJSYS03 220, 226
- IMPLEN, FLAG assembler suboption 54
- INCLUDE control statement 177, 231
- INEXIT
  - EXIT assembler suboption 51
  - installation option 53
- INFO assembler option 59
- input, binder (z/OS) 176
- input, linkage editor 229
- installation and customization
  - book information xii
- invoking cataloged procedures 184
- invoking the assembler from a problem program 222
- invoking the assembler from a program (z/OS) 164

## J

- JP, LANGUAGE assembler suboption 60

## L

- LANGUAGE assembler option 60
- Language Reference xii
- LET binder option 179
- LIBEXIT
  - EXIT assembler suboption 51
  - installation option 53
- LIBMAC assembler option 60
- Library 226, 227
- LIBRARY control statement 177
- LIBRARY exit processing 106
- license inquiry 441
- Licensed Program Specifications xii
- LIMIT installation option 83
- LIMIT, USING assembler suboption 81
- LINECOUNT assembler option 61
- LINK macro instruction (z/OS) 164
- linkage conventions for external functions 146
- linkage editor
  - control statements 231
  - errors 232
  - files 230

linkage editor (*continued*)

- INCLUDE statement 231
- input 229
- libraries 231
- output 232
- sample 229
- z/OS
  - AMODE option 179
  - CALL option 179
  - errors 181
  - LET option 179
  - MAP option 179
  - PRINT option 179
  - RMODE option 179
  - TSO LINK command 180
- linkage, object program 194
- linker
  - definition 446
- Linux
  - overview 433
- LIST assembler option 61, 224
- LIST binder option 178
- LIST, OPTABLE assembler suboption 66
- listing control instructions, printing of 17
- LISTING exit processing 112
- listing format 12
- LITTYPE, COMPAT assembler suboption 47
- LKED command (CMS) 210
- LOAD command (CMS) 209
- load module
  - on TSO 175
  - sample 175
- load module modification 195
- loader 174
- loading user exits 89
- LOADLIB (CMS) 210
- logical saved segments (CMS) 73
- LRECL for assembler files 227
  - CMS 204
  - z/OS 169

## M

- MACHINE assembler option 62
- machine instructions 257
- machine instructions, publications 451
- macro and copy code cross reference
  - listing format 26
- macro and copy code cross reference with LIBMAC option 27
- macro and copy code source summary
  - listing format 25
- macro definition libraries, additions to 233
  - CMS 213
  - z/OS 183
- macro-generated statements
  - format of 17
  - in diagnostic messages 338
- MACROCASE, COMPAT assembler suboption 47
- macros
  - ASMADATA 267, 389
  - ASMAEFNP 146, 389
  - ASMAXFMB 389

macros (*continued*)

- ASMAXITP 90, 389
- macros, error messages in 153
- macros, external function calls 145
- MAGNITUDE, TYPECHECK assembler suboption 79
- manuals, High Level Assembler xii
- map
  - link-edit option 232
- MAP
  - binder option (z/OS) 178
  - processing option 179
- MAP installation option 83
- MAP, USING assembler suboption 81
- MAX
  - LIST assembler option 61
  - SIZE assembler option 74
- MCALL, PCONTROL assembler suboption 67
- message code format 335
- messages 435
- MHELP
  - description 157
  - global suppression—operand=32 325
  - macro AIF dump—operand=4 325
  - macro branch trace—operand=2 325
  - macro call trace—operand=1 325
  - macro entry dump—operand=16 325
  - macro exit dump—operand=8 325
  - macro hex dump—operand=64 325
  - MHELP control on &SYSNDX 326
  - MHELP
    - suppression—operand=128 325
    - sample program and listing 325
- MHELP instruction
  - format 157
- migration considerations 5
- migration to High Level Assembler 239
- MNOTE statements 155
- MSOURCE, PCONTROL assembler suboption 67
- MVS/ESA
  - assembling on 161
- MXREF assembler option 64

## N

- National Language Support 60
- NOADATA assembler option 433
- NOADEXIT, EXIT assembler suboption 51
- NOALIGN
  - assembler option 44, 224
  - FLAG assembler suboption 54
- NOASA assembler option 45
- NOASA assembler option (CMS) 204
- NOASA assembler option (z/OS) 169
- NOBATCH assembler option 45
- NOCALL link-edit option 179
- NOCASE, COMPAT assembler suboption 47
- NOCOMPAT assembler option 47
- NOCONT, FLAG assembler suboption 54
- NODATA, PCONTROL assembler suboption 67
- NODBCS assembler option 48



- NODECK assembler option 48, 224, 433
- NODXREF assembler option 49
- NOERASE assembler option (CMS) 49
- NOESD assembler option 50
- NOEXIT assembler option 51
- NOEXLITW, FLAG assembler suboption 54
- NOFOLD assembler option 57
- NOGEN, PCONTROL assembler suboption 67
- NOGOFF assembler option 57, 433
- NOIMPLEN, FLAG assembler suboption 54
- NOINEXIT, EXIT assembler suboption 51
- NOINFO assembler option 59
- NOLET binder option 179
- NOLIBEXIT, EXIT assembler suboption 51
- NOLIBMAC assembler option 60
- NOLIMIT, USING assembler suboption 81
- NOLIST assembler option 61, 224
- NOLIST, OPTABLE assembler suboption 66
- NOLITYPE, COMPAT assembler suboption 47
- NOMACROCASE, COMPAT assembler suboption 47
- NOMAGNITUDE, TYPECHECK assembler suboption 79
- NOMAP
  - binder option 179
  - USING assembler suboption 81
- NOMCALL, PCONTROL assembler suboption 67
- NOMSOURCE, PCONTROL assembler suboption 67
- NOMXREF assembler option 64
- NOOBJECT assembler option 65, 224, 433
- NOOBJEXIT, EXIT assembler suboption 51
- NOPAGE0, FLAG assembler suboption 54
- NOPCONTROL assembler option 67
- NOPRINT assembler option (CMS) 69
- NOPRINT binder option 179
- NOPROFILE assembler option 70
- NOPRTEXT, EXIT assembler suboption 51
- NOPUSH, FLAG assembler suboption 54
- NORA2 assembler option 71
- NORECORD, FLAG assembler suboption 54
- NOREGISTER, TYPECHECK assembler suboption 79
- NORENT assembler option 71
- NORLD assembler option 72, 224
- NORXREF assembler option 72
- NOSEG assembler option 73
- NOSUBSTR, FLAG assembler suboption 54
- NOSUPRWARN assembler option 76
- NOSYSLIST, COMPAT assembler suboption 47

- notation, description xiii
- NOTERM assembler option 77, 224
- NOTEST assembler option 78
- NOTHREAD assembler option 78
- NOTRANSLATE assembler option 79
- NOTRMEXIT, EXIT assembler suboption 51
- NOTYPECHECK assembler option 79
- NOUHEAD, PCONTROL assembler suboption 67
- NOUSING assembler option 81
- NOUSING0, FLAG assembler suboption 54
- NOWARN, USING assembler suboption 81
- NOWORKFILE assembler option 83
- NOXOBJECT assembler option 84
- NOXREF assembler option 84, 224

## O

- object
  - extended format 84
  - file format 58, 259, 446
  - modules 177, 230, 231, 257
  - program linkage 194
  - program migration 5
- OBJECT assembler option 58, 65, 224, 433
- OBJECT exit processing 116
- OBJEXIT
  - EXIT assembler suboption 51
  - installation option 53
- OFF, PCONTROL assembler suboption 67
- ON statement 228
- ON, PCONTROL assembler suboption 67
- online publications xiii
- OPEN calls to user exit 92
- OPTABLE assembler option 66
- option summary listing format 8
- options
  - binder (z/OS) 178
  - ELF32 433
  - EXIT 433
  - NOADATA 433
  - NODECK 433
  - NOGOFF 433
  - NOOBJECT 433
  - not available 433
  - OBJECT 433
  - SIZE 433
  - sources 433
- options file
  - overriding \*PROCESS OVERRIDE option 40
- options library member
  - overriding \*PROCESS OVERRIDE option 40
- ordinary symbol and literal cross reference 22, 84
- organization of this document x
- OSRUN command (CMS) 210
- output format listing 12
- output, linkage editor 232
- OVERRIDE on \*PROCESS statement 41

- overriding ddname 165
- overriding default options 42, 190
- overriding statements in cataloged procedures 190

## P

- PAGE0, FLAG assembler suboption 54
- PARM field 39
- Part Reference, definition 447
- partitioned data set definition 447
- PCONTROL assembler option 67
- PDSE definition 447
- PESTOP assembler option 69
- phase
  - create 229
  - sample 229
- portability
  - machine instructions 257
  - object modules 257
  - system macros 257
- precedence of assembler options 39
- primary binder data set 176
- PRINT assembler option (CMS) 69
- PRINT binder option 179
- PROCESS calls to user exit 92
- PROCESS COPY calls to user exit 92
- PROCESS MACRO calls to user exit 92
- processing E-Decks 233
- processor time for the assembly 36
- PROFILE assembler option 70
- PROFMEM, default profile member name 70
- program execution 181
- program fetch definition 448
- program library definition 448
- program management binder definition 448
- program module definition 448
- program module modification 195
- program object, definition 448
- program termination 234
  - CMS 214
  - z/OS 193
- program type 22, 24
- Programmer's Guide xii
- PRTEXT
  - assembler suboption 51
  - installation option 53
- publications
  - High Level Assembler xii, 451
  - HLASM Toolkit 451
  - machine instructions 451
  - online (CD-ROM) xiii
  - z/OS 451
  - z/VM 451
  - z/VSE 452
- PUNCH exit processing 116
- PUSH
  - FLAG assembler suboption 54
  - level, in the assembler listing 19

## R

- RA2 assembler option 71
- railroad track format, how to read xiii

- range, in USING Map 31
- READ calls to user exit 92
- RECFM for assembler files 227
  - CMS 204
  - z/OS 169
- RECORD, FLAG assembler suboption 54
- RECORDINFO installation option 57
- reference information for statements in error 156
- register cross reference 32
- REGISTER, TYPECHECK assembler suboption 79
- registers, saving and restoring
  - CMS 213
  - z/OS 193, 195
  - z/VSE 234
- REINIT calls to user exit 92
- relocation dictionary
  - examples 12, 319
  - listing format 21
- RENT assembler option 71
- request information list
  - ASMAXITP mapping macro 431
- residency mode 180
- restoring registers
  - CMS 213
  - z/OS 193
  - z/VSE 234
- return codes 171, 228
- RETURN macro instruction
  - CMS 213
  - z/OS 193
  - z/VSE 234
- RLD assembler option 72, 224
- RLD Record format 261
- RMODE
  - binder option 179
  - in ESD section of listing 14
  - processing option 180
- RSECT instruction
  - interaction with GOFF 58
- running
  - CMS 209
  - TSO 182
  - using batch facility 210
  - using LKED and OSRUN commands 210
  - using LOAD and START commands 209
  - using the GENMOD command 209
  - z/OS 181
- running programs on CMS 209
- running your program 232
- RXREF assembler option 72

## S

- S370, MACHINE assembler suboption 62
- S370ESA, MACHINE assembler suboption 62
- S370XA, MACHINE assembler suboption 62
- S390, MACHINE assembler suboption 62

- S390E, MACHINE assembler suboption 62
- sample ADATA user exits 391
- sample LISTING user exit 403
- sample program to call the assembler dynamically 223
  - z/OS 166
- sample programs and listings
  - assembler language features, using 313
  - assembler listing description 8
  - diagnostic error messages 156
  - MHELP 325
- sample SOURCE user exit 405
- SAVE macro instruction
  - CMS 213
  - z/OS 193
  - z/VSE 234
- saving registers
  - CMS 213
  - z/OS 193
  - z/VSE 234
- secondary data set 176
- SECTALGN assembler option 73
- section, definition 448
- SEG assembler option 73
- segment, definition 448
- sequence number 17
- SHORT, XREF assembler suboption 84
- SIZE assembler option 74, 433
- softcopy publications xiii
- source and object assembler listing format 14
- source and object listing 14
- source and object listing, 121 character format 15
- source and object listing, 133 character format 20
- SOURCE exit processing 104
- source program migration 5
- SOURCE, MXREF assembler suboption 64
- stacked items xiv
- START command (CMS) 209
- start time of assembly 36
- Static Assembler information block 99
- Static Assembler Information Pointer 99
- statistics, assembler 36
- stop time of assembly 36
- SUBLIB JCL option 227
- SUBSTR, FLAG assembler suboption 54
- suppression of error messages and MNOTE statements 156
- SUPRWARN assembler option 76
- SYM Record format 263
- syntax notation, description xiii
- SYSADAT 226, 228
- SYSADATA data set 167, 171
- SYSADATA file 203, 207
- SYSIN data set 167, 170
- SYSIN file 203, 205
- SYSIPT 226, 227, 231
- SYSLIB data set 167, 170, 177
- SYSLIB file 203, 206
- SYSLIN data set 167, 171, 177
- SYSLIN file 203, 207

- SYSLIST, COMPAT assembler suboption 47
- SYSMOD data set 177
- SYSLNK 220, 226, 228, 230, 231
- SYSLOG 226, 227, 231
- SYSLST 226, 227, 231
- SYSARM assembler option 76
- SYSPPCH 226, 228
- SYSPPRINT data set 167, 170, 177
- SYSPPRINT file 203, 206
- SYSPPUNCH data set 167, 171
- SYSPPUNCH file 203, 207
- SYSRDR 231
- system macros 257
- system variable symbols
  - comparison with earlier assemblers 242
  - in diagnostic messages 338
  - MHELP numbering system 325
  - setting data set information 102
- system-determined blocksize 169
- SYSTEM data set 167, 170, 177
- SYSTEM file 203, 206
- SYSUT1 data set 177

## T

- TERM assembler option 77, 224
- TERM exit processing 123
- termination
  - abnormal assembly 156
  - program 234
    - CMS 214
    - z/OS 193
- TEST assembler option 78
- text, definition 448
- THREAD assembler option 78
- Toolkit Customization book xiii
- Toolkit installation and customization
  - book information xiii
- TRANSLATE assembler option 79
- translation table generation 407
- TRMEXIT
  - EXIT assembler suboption 51
  - installation option 53
- TSO
  - assembling on 163
  - LINK command 180
  - link-edit options 180
  - running 182
- TXT Record format 261
- TYPECHECK assembler option
  - description 79, 415

## U

- UE, LANGUAGE assembler suboption 60
- UHEAD, PCONTROL assembler suboption 67
- UNI, OPTABLE assembler suboption 66
- Unicode translation table generation 409
- unreferenced symbols defined in CSECTs 84
- unreferenced symbols defined in CSECTs
  - listing format 25

UNREFS, XREF assembler suboption 84  
user exit

- ADATA exit processing 120
- addressing mode (AMODE) 90
- ASMAXADC (ADATA user exit) 397
- ASMAXADR (ADATA user exit) 399
- ASMAXADT (ADATA user exit) 391
- ASMAXFMB (ADATA user exit) 391
- ASMAXFMT (ADATA user exit) 391
- ASMAXINV (SOURCE user exit) 405
- ASMAXPRT (LISTING user exit) 403
- calling 90
- coding example 126
- error handling 100
- EXIT assembler option 51
- exit parameter list 90
- exit-specific information block 90, 101
- failure handling 100
- filter management table (ADATA user exit) 391
- filter modules (ADATA user exit) 391
- LIBRARY exit processing 106
- linkage conventions 90
- LISTING exit processing 112
- loading 89
- locating 89
- OBJECT exit processing 116
- PUNCH exit processing 116
- reason codes 95
- residency mode (RMODE) 90
- return codes 94
- sample ADATA user exit 391, 397, 399
- sample LISTING user exit 403
- sample SOURCE user exit 405
- samples 126
- SOURCE exit processing 104
- specifying 88
- TERM exit processing 123
- types 87
- user error handling 100
- user exits 434
- user-specified data set 177
- USING assembler option 81
- USING map listing format 30
- using the assembler 219
  - CMS 199
  - TSO 163
  - z/OS 161
  - z/VSE 219
- using the assembler (ICCF) 220
- USING0, FLAG assembler suboption 54
- USINGs, active
  - in the assembler listing 19
  - UHEAD, PCONTROL assembler suboption 67
- utility data set 167
- utility file 203, 226

## V

variable symbols, system  
comparison with earlier  
assemblers 242

## W

WARN

- installation option 83
- USING assembler suboption 81

WORKFILE assembler option 83  
WRITE calls to user exit 92

## X

XA, OPTABLE assembler suboption 66  
XCTL macro instruction (z/OS) 164  
XOBJECT assembler option 84  
XREF assembler option 84, 224  
XREF binder option (z/OS) 178  
XREF, MXREF assembler suboption 64

## Z

z/OS

- assembler macros supported by 183
- running 181

z/OS publications 451  
z/VM publications 451  
z/VSE

- JCL options 224
- relationship to assembler 219
- running your program 232

z/VSE publications 452  
ZOP, OPTABLE assembler suboption 66  
ZS-2, MACHINE assembler suboption 62  
ZS-3, MACHINE assembler suboption 62  
ZS-4, MACHINE assembler suboption 62  
ZS, MACHINE assembler suboption 62  
ZS3, OPTABLE assembler suboption 66  
ZS4, OPTABLE assembler suboption 66  
ZSERIES-2, MACHINE assembler suboption 62  
ZSERIES-3, MACHINE assembler suboption 62  
ZSERIES-4, MACHINE assembler suboption 62  
ZSERIES, MACHINE assembler suboption 62





---

## Readers' Comments — We'd Like to Hear from You

High Level Assembler for z/OS & z/VM & z/VSE  
Programmer's Guide  
Release 6

Publication No. SC26-4941-05

We appreciate your comments about this publication. Please comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. The comments you send should pertain to only the information in this manual or product and the way in which the information is presented.

For technical questions and information about products and prices, please contact your IBM branch office, your IBM business partner, or your authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you. IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you state on this form.

Comments:

Thank you for your support.

Send your comments to the address on the reverse side of this form.

If you would like a response from IBM, please fill in the following information:

\_\_\_\_\_  
Name

\_\_\_\_\_  
Address

\_\_\_\_\_  
Company or Organization

\_\_\_\_\_  
Phone No.

\_\_\_\_\_  
E-mail address



Cut or Fold  
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES

**BUSINESS REPLY MAIL**

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation  
Reader Comments  
DTX/E269  
555 Bailey Avenue  
San Jose, CA  
U.S.A. 95141-9989



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold  
Along Line





Program Number: 5696-234

Printed in USA

SC26-4941-05

