

IBM Maximo for Oil and Gas 7.6.1
Version 7 Release 6

Installation Guide



Note

Before using this information and the product it supports, read the information in “Notices” on page 13.

This edition applies to version 7, release 6 modification 1 of IBM Maximo for Oil and Gas and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright IBM Corporation 2007, 2016.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Chapter 1. Planning to deploy IBM

Maximo for Oil and Gas 1

System requirements for Maximo for Oil and Gas . . 1

Chapter 2. Installing Maximo for Oil and Gas 3

Automatically updating the database and building and deploying the EAR file 4

Manually updating the database and building and deploying the EAR file 4

 Updating the database and building the EAR file 4

 Deploying the EAR file on WebSphere Application Server 5

 Command syntax for deploying EAR files on WebSphere Application Server 5

 Deploying the EAR file on WebLogic Server . . 6

Installing the Maximo Incident Reporter mobile app 6

 Maximo Incident Reporter security group. . . . 7

Installing silently 7

 Installing Maximo for Oil and Gas silently . . . 8

 Silent mode: Installing the mobile app. 8

Enabling the features of Maximo Spatial Asset

Management 9

 Granting access rights to users of Maximo Spatial

 Asset Management 10

Installing help locally 11

Notices 13

Trademarks 15

Terms and conditions for product documentation. . 15

IBM Online Privacy Statement 16

Index 17

Chapter 1. Planning to deploy IBM Maximo for Oil and Gas

IBM® Maximo® for Oil and Gas 7.6.1 must be installed with IBM Maximo Asset Management 7.6.0.6.

System requirements for Maximo for Oil and Gas

Before you install Maximo for Oil and Gas, your environment must meet all of the hardware and software requirements.

Enterprise system

You install Maximo for Oil and Gas 7.6.1 on the administrative workstation where Maximo Asset Management 7.6.0.6 is installed.

Mobile app

Before you install the mobile app, you must install IBM Maximo Anywhere 7.6.1 or a later version. Maximo Anywhere includes required components that must be installed on the Maximo for Oil and Gas administrative workstation. The required components include OSLC object structures and licenses that enable a set of applications in Maximo Asset Management.

As part of the app installation, you must deploy another collection of required components on the Maximo for Oil and Gas administrative workstation.

A complete list of hardware and software requirements is available in the System Requirements section of the Maximo Asset Management wiki (www.ibm.com/developerworks/community/wikis/home?lang=en#!/wiki/IBM%20Maximo%20Asset%20Management/page/Other%20Maximo%20products%20system%20requirements).

Chapter 2. Installing Maximo for Oil and Gas

You must install Maximo for Oil and Gas in the same program group where Maximo Asset Management is installed.

Before you begin

Ensure that IBM Maximo Asset Management 7.6.0.6 is installed on the computer where you are installing Maximo for Oil and Gas 7.6.1.

For more information, see the installation topics for Maximo Asset Management 7.6.0.6 IBM Knowledge Center (www.ibm.com/support/knowledgecenter/SSLKT6_7.6.0.6/com.ibm.mam.doc/welcome.html).

For information about upgrading to Maximo Asset Management 7.6 from an earlier version of Maximo Asset Management, see the Maximo Upgrade Resources website (www.ibm.com/support/docview.wss?uid=swg21266217).

About this task

The configuration tool is launched automatically when the installation wizard is complete. It is called IBM Tivoli®'s process automation engine configuration tool.

After you are done using the configuration tool, the Maximo for Oil and Gas application starts automatically.

Procedure

1. Download the Maximo for Oil and Gas product software from IBM Passport Advantage® and extract the installation image to a local directory.
2. Start the launchpad by double-clicking the launchpad file.

Option	Description
Windows	launchpad64.exe
UNIX or Linux	launchpad.sh

3. On the Install IBM Maximo for Oil and Gas pane, click **Install**.
4. Depending on the package that you are installing, you might be required to click **Install** or **Update** and click **Next**.
5. After you accept the terms in the license agreement, select the option to use the existing package group **IBM Tivoli's automation suite**.
6. Complete the installation wizard.
7. In the configuration tool, select **Update the database with the UpdateDB Lite feature**.
8. Verify the application version and current state.
9. To complete the deployment, run both the pre-processing and post-processing options, and click **Finish**.
10. When the installation is complete, verify that the Maximo for Oil and Gas component was installed. Log in to Maximo for Oil and Gas and view the system information from the **Help** menu.

What to do next

When the installation and configuration steps are complete, you can configure Maximo for Oil and Gas to meet your business needs.

Automatically updating the database and building and deploying the EAR file

If you deferred the configuration step during installation, you can use the configuration tool to update the Maximo database and build and deploy the EAR file.

Before you begin

Ensure that the installation of Maximo for Oil and Gas is complete.

About this task

If you do not wish to use the configuration tool, you can use the command line tool to perform the same operations. For more information, see [Command line configuration \(www.ibm.com/support/knowledgecenter/SSLKT6_7.6.0.5/com.ibm.mam.inswas.doc/install/c_IntroductionToTheCommandLineConfigurationProgram.html\)](http://www.ibm.com/support/knowledgecenter/SSLKT6_7.6.0.5/com.ibm.mam.inswas.doc/install/c_IntroductionToTheCommandLineConfigurationProgram.html).

Procedure

1. Start the configuration tool by double-clicking the ConfigUI file in the *install_home/ConfigTool* directory.
2. On the home screen of IBM Tivoli's process automation engine configuration tool, select **Update the database with the UpdatedDB Lite feature**.
3. Complete the screens in the configuration tool.

Manually updating the database and building and deploying the EAR file

If you do not use the configuration tool, you must manually update the Maximo database and build and deploy the EAR file. If your deployment uses Oracle WebLogic Server, you are required to complete the manual steps.

Updating the database and building the EAR file

To deploy the product, you must update the Maximo database and build and deploy the Maximo EAR file.

Procedure

1. Open a command prompt and change to the *install_home\maximo\tools\maximo* directory.
2. Run the following command:
`updatedb`
3. If languages other than English are installed on the system, run the following command:
`<install_home>\maximo\tools\maximo\TDToolkit.bat -pmpupdateoilandgas -useexpander`
4. Change to the *install_home\maximo\deployment* directory and run the following command:

Option	Description
WebSphere Application Server	buildmaximoearwas8
Oracle Web Logic Server	buildmaximoear

Deploying the EAR file on WebSphere Application Server

If you did not use the configuration tool, Maximo Asset Management includes a command line tool, which you can use to manually deploy the EAR file.

Before you begin

- Update the Maximo database and build the EAR file.
- Ensure that the application server is started.

About this task

The EAR file is installed on WebSphere® Application Server during the Maximo Asset Management installation.

Deploying the EAR file starts the application server.

Procedure

1. Open a command prompt and change to the *install_home\ConfigTool\scripts* directory.
2. On Windows systems, run the following commands:

```
reconfigurePae.bat -action configureProductsDBLite -preprocessor -buildears
reconfigurePae.bat -action configureProductsDBLite -updatedb -deploymaximoear
```

On UNIX or Linux systems, run the following commands:

```
reconfigurePae.sh -action configureProductsDBLite -preprocessor -buildears
reconfigurePae.sh -action configureProductsDBLite -updatedb -deploymaximoear
```

Command syntax for deploying EAR files on WebSphere Application Server

You use parameters in the command syntax when you manually deploy the EAR files on WebSphere Application Server.

Parameters

WASAdminUserName

A WebSphere Application Server Network Deployment account with deployment privileges.

WASAdminPassword

The password of the user who is specified in the *WASAdminUserName* parameter.

WASNodeName

The name of the WebSphere Application Server Network Deployment node.

WASApplicationServerName

The name of the WebSphere Application Server Network Deployment application server.

WASVirtualHost

The name of the WebSphere Application Server Network Deployment virtual host.

WASWebServerName

The name of the WebSphere Application Server Network Deployment web server.

Deploying the EAR file on WebLogic Server

After you build the EAR file, you must deploy it from the WebLogic Server console.

Before you begin

- Update the Maximo database and build the EAR file.
- On Windows: If the MAXIMOSERVER server is not running, start it from a command prompt.
- On UNIX: Ensure that the WebLogic Server daemon is running.

To view the WebLogic Server console, a Java™ virtual machine must be installed.

About this task

The Maximo EAR file is installed on WebLogic Server during the Maximo Asset Management installation.

Deploying the EAR file starts the application server.

Procedure

1. Open a command prompt and change to the mydomain directory.
 - On Windows systems, the directory path is *weblogic_home\user_projects\domain\mydomain*.
 - On UNIX or Linux systems, the directory path is *weblogic_home/mxadmin/oracle/user_projects/domains/mydomain*.
2. Start WebLogic Server.

Option	Command
Windows	startWebLogic.cmd
UNIX or Linux	./startWebLogic.sh

3. Specify the WebLogic Server user name and password.
4. Log in to the WebLogic Server console at <http://hostname:7001/console>.
5. In the WebLogic Server console, follow the instructions to deploy the maximo.ear file.

Installing the Maximo Incident Reporter mobile app

The installation process involves running the installation and configuration programs on one or more computers.

Before you begin

Ensure that you have installed IBM Maximo Anywhere 7.6.1 or a later version on the computer where Maximo for Oil and Gas is installed.

If you plan to install the Maximo for Oil and Gas mobile app on a designated build computer, copy the app and the Maximo Anywhere compressed file to the target computer.

Before you can build and deploy the Maximo® Incident Reporter mobile app on the build computer, your system requires either the Android, iOS, or Windows development tools.

Note: The Maximo Incident Reporter mobile app is not supported on Windows RT on Tablet. The Maximo Incident Reporter app is not supported on Windows Phones. Windows Tablet OS 8.1 is supported, but Windows Tablet OS 8.0 is not supported.

About this task

A set of required components must be installed on the administrative workstation to extend Maximo for Oil and Gas for mobile apps.

Procedure

1. On the Maximo for Oil and Gas computer, extract the compressed file that contains the mobile app.
2. From the extracted file, start the launchpad.
3. On the Install IBM Maximo Incident Reporter 7.6.1 pane, click **Install IBM Maximo Asset Management Required Components** and complete the installation wizard.
4. In Tivoli's process automation engine configuration tool, select **Update Database and Build and Deploy Application EAR File** and complete the configuration tool.
5. To install the mobile app on the computer where Maximo Anywhere is installed, copy the compressed file for the mobile app to the target computer.
6. On the Maximo Anywhere computer, extract the compressed file to a local directory.
7. From the extracted file, start the mobile app launchpad.
8. On the launchpad pane for installing the mobile app, click **Install**.
9. Complete the installation wizard.
10. Build and deploy the mobile app by following the instructions in IBM Knowledge Center (www.ibm.com/support/knowledgecenter/SSPJLC_7.6.1/com.ibm.si.mpl.doc/build_deploy/t_ctr_build_deploy_apps.html).

Related information:

Preparing the Maximo Anywhere environment

Maximo Incident Reporter security group

When mobile workers manage records, they must have the authority to use the Maximo® Incident Reporter mobile app. You authorize access to the Maximo Incident Reporter mobile app by adding users to the predefined security group in Maximo Asset Management.

For the Maximo Incident Reporter mobile app, you add the Anywhere Incident Security Group: ANYWHERE_INCIDENT_GROUP.

Related information:

Adding users to the Maximo Anywhere security groups

Installing silently

A silent installation is useful for installing the product components on any computers that are configured in the same way.

Installing Maximo for Oil and Gas silently

Instead of using the installation programs, you can run commands by using a generated response file from the initial installation of Maximo for Oil and Gas.

Before you begin

To create a response file during the installation of Maximo for Oil and Gas, open a command prompt and set the **record** environment variable to true. Then, start the Maximo for Oil and Gas launchpad. The response file is generated in the home directory of the user ID that started the program.

Alternatively, you can modify one of the sample response files that are provided in the installation image.

Ensure that the values in the response file are valid for the target system. The **installLocation** parameter and the **profile id** parameter must correspond with the existing Maximo Asset Management instance.

Procedure

1. Copy the response file and the compressed installation image to the target computer.
2. On the target computer, open a command prompt and change directory to the location of the Installation Manager program.

Option	Description
Windows	cd C:\SMP\IBM\InstallationManager\ eclipse\tools\
Linux and UNIX	cd /opt/IBM/InstallationManager/eclipse/ tools/

3. Silently start Installation Manager by running the following command:

```
imcl -input responsefilename  
-log logfilename-acceptLicense
```

The **-input** parameter determines the path to the response file and the **-log** parameter determines the path to where the log files are written. The **-acceptLicense** parameter is used to accept the license automatically. For example, run the following command:

```
imcl -silent -input C:\tmp\OilAndGas_Silent_ResponseFile.xml  
-log C:\tmp\silent_install_log.xml -acceptLicense
```

Results

The installation proceeds silently with the values that you provided in the response file. By using different response files as input, you can silently install middleware on separate systems.

Silent mode: Installing the mobile app

Instead of using the installation programs, you can install the required components and the app by running commands and sample response files.

Before you begin

The response files are provided in the app installation images. One response file is used to install the required components on the Maximo for Oil and Gas computer. The other response file is used to install the mobile app on the Maximo Anywhere computer.

Ensure that the values in the response file are valid for the target system. The **installLocation** parameter and the **profile id** parameter must correspond with the existing Maximo Asset Management instance.

About this task

This silent installation procedure has the same requirements as a non-silent installation of the mobile app.

Procedure

1. On the computer where Maximo for Oil and Gas 7.6.1 is installed, extract the compressed installation image.
2. Open a command prompt and change directory to the location of the Installation Manager program.

Option	Description
Windows	cd C:\Program Files\IBM\InstallationManager\eclipse\tools\
Linux and UNIX	cd /opt/IBM/InstallationManager/eclipse/tools/

3. Silently start Installation Manager by running the following command:

```
imcl -input responsefilename  
-log logfile -acceptLicense
```

The **-input** parameter determines the path to the response file and the **-log** parameter determines the path to where the log files are written. The **-acceptLicense** parameter is used to accept the license automatically. For example, run the following command:

```
imcl -input C:\tmp\<app_name>_IncidentReporter_Silent_ResponseFile.xml  
-log C:\tmp\silent_install_log.xml -acceptLicense
```

4. To install the mobile app on the computer where Maximo Anywhere is installed, copy the compressed installation images to the target computer.
5. Extract the compressed file and repeat steps 2-3. Replace the response file name in the command with the *<app_name>_Anywhere_IncidentReporter_App_Silent.xml* file.

Related tasks:

Silent mode: Installing Maximo Anywhere

Enabling the features of Maximo Spatial Asset Management

If a license for Maximo Spatial Asset Management is installed and enabled, you must modify the *oilandgas.xml* file to use the spatial features.

About this task

Modify the `oilandgas.xml` file to add the **Map (Spatial)** tab to the following applications:

- Assets (Oil)
- Locations (Oil)
- Service Requests (Oil)
- Work Order Tracking (Oil)

Procedure

1. Edit the `oilandgas.xml` file to remove the comment tags (`<!--` and `-->`) from each of the following elements:

```
<extendpresentation app='PLUSGWO' baseapp='WOTRACK' product='spatial'>
```

```
<extendpresentation app='PLUSGSR' baseapp='SR' product='spatial'>
```

```
<extendpresentation app='PLUSGASS' baseapp='ASSET' product='spatial'>
```

```
<extendpresentation app='PLUSGLOC' baseapp='LOCATION' product='spatial'>
```

The `oilandgas.xml` file is in the `install_home\maximo\applications\maximo\properties\product` directory.

2. Run the following command: **updatedb**
3. Build the EAR file.
4. Deploy the EAR file for your application server:
 - Deploy the EAR file on WebLogic Server.
 - Deploy the EAR file on WebSphere Application Server
5. Grant access to the Maximo Spatial Asset Management options.

Granting access rights to users of Maximo Spatial Asset Management

The system administrator or the group of users who use Maximo Spatial Asset Management must have access to the Maximo Spatial Asset Management options. You grant access rights in the Security Groups application.

Before you begin

Maximo for Oil and Gas and Maximo Spatial Asset Management must be installed and the features of Maximo Spatial Asset Management must be enabled.

Procedure

1. Log in to Maximo Asset Management and in the Security Groups application, open the MAXADMIN user group.
2. On the Applications tab, select the Assets (Oil) application, grant access for the following options, and save the group record:
 - Master Work Order And One Work Order for Each Record
 - Service Request With All Records
 - Spatial Edit Tool
 - Spatial Link Tool
 - Work Order for Each Record
 - Work Order for All Records

3. Select the Locations (Oil) application, grant access for the following options, and save the group record:
 - Master Work Order And One Work Order for Each Record
 - Service Request With All Records
 - Spatial Edit Tool
 - Spatial Link Tool
 - Work Order for Each Record
 - Work Order for All Records
4. Select the Work Order Tracking (Oil) application, grant access for the following options, and save the group record:
 - Auto-Create WO (Spatial)
 - Spatial Edit Tool
 - Spatial Link Tool
5. Close the session and log in again to apply the changes.

Results

The Maximo Spatial Asset Management options are shown in the Assets (Oil), Locations (Oil), Service Requests (Oil), and Work Order Tracking (Oil) applications.

Installing help locally

Product help for Maximo for Oil and Gas is provided online in IBM Knowledge Center. If you want to install help locally, you can download IBM Knowledge Center and help packages from Fix Central.

To download a locally-installable version of IBM Knowledge Center and help packages from Fix Central, follow the instructions at <http://www-01.ibm.com/support/docview.wss?uid=swg24041962>

Notices

This information was developed for products and services that are offered in the USA. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those

websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other product and service names might be trademarks of IBM or other companies.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

IBM Online Privacy Statement

IBM Software products, including software as service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth in the following section.

Depending upon the configurations deployed, this Software Offering may use session and persistent cookies that collect each user's name, user name, password, or other personally identifiable information for purposes of session management, authentication, single sign-on configuration or other usage tracking or functional purposes. These cookies can be disabled, but disabling them will also likely eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> in the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

Index

B

building
 EAR file 4

D

deploying
 EAR file 4, 5, 6
deployment
 planning 1

E

enabling Maximo Spatial Asset
 Management features 10

G

granting access rights 10

I

installing
 Maximo for Oil and Gas 3
 Maximo Incident Reporter mobile
 app 6

M

Maximo database 4

S

security groups 10
silently installing
 Maximo for Oil and Gas 8
 mobile apps 9

U

updating
 Maximo database 4

W

WebLogic Server 6
WebSphere Application Server 5



Printed in USA