

z/OS



JES2 Initialization and Tuning Guide

z/OS



JES2 Initialization and Tuning Guide

Note

Before using this information and the product it supports, be sure to read the general information under "Appendix D. Notices" on page 411.

First Edition, March 2001

This edition applies to Version 1 Release 1 of z/OS (5694-A01) and to all subsequent releases and modifications until otherwise indicated in new editions.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

IBM welcomes your comments. A form for readers' comments may be provided at the back of this publication, or you may address your comments to the following address:

International Business Machines Corporation
Department 55JA, Mail Station P384
2455 South Road
Poughkeepsie, NY 12601-5400
United States of America

FAX (United States & Canada): 1+845+432-9405

FAX (Other Countries):

Your International Access Code +1+845+432-9405

IBMLink (United States customers only): IBMUSM10(MHVRCFS)

Internet e-mail: mhvrfs@us.ibm.com

World Wide Web: <http://www.ibm.com/servers/eserver/zseries/zos/webqs.html>

If you would like a reply, be sure to include your name, address, telephone number, or FAX number.

Make sure to include the following in your comment or note:

- Title and order number of this book
- Page number or topic related to your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1988, 2001. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures.	xi
Tables.	xiii
About This Book.	xv
Who Should Use This Book	xv
How to Use This Book	xv
3800 Printer	xv
Where to Find More Information.	xv
Using LookAt to look up message explanations.	xvi
Additional Information	xvii

Part 1. JES2 Initialization 1

Chapter 1. JES2 Initialization	3
Installation Overview	3
Service Considerations	3
JES2 Initialization Process Overview	3
Modifying How JES2 Performs Initialization	4
JES2 Sample Initialization Data Sets	5
Initialization Statements and Parameters	6
Defining JES2 to the Cross-System Coupling Facility (XCF)	9
How JES2 Determines the JES2 XCF Group Name	9
XCF Group Name Restrictions	10
How JES2 Determines the JES2 XCF Group Member Name	10
Defining JES2 Structures in a CFRM Policy	11
How to Control JES2 Initialization	11
Creating an Initialization Data Set	12
Sample JES2 Initialization Data Set and HASPLIST Corrections	16
Creating the JES2 Cataloged Procedure	23
Specifying User PROCLIBs in the JES2 Cataloged Procedure	25
Defining the Data Set for JES2 Initialization Parameters	26
Specifying the Start Options	27
Controlling Initialization Using JES2 Exits and the \$SCAN Facility	32
Controlling JES2 Load Modules	32
JES2 Load Modules	32
Loading JES2 Subsystem Support Modules	33
JES2 Subsystem Module Placement and Storage Considerations	34
Controlling the Loading of Installation-Defined Load Modules	34
Starting and Stopping JES2	35
JES2 Program Properties	35
Starting JES2 for the First Time (A Cold Start)	36
Performing an Orderly Shutdown of a JES2 Member	38
SMF Record Summary: Starting and Stopping JES2	39
Using Event Notification Signalling with JES2	40
Restarting JES2	40
Cold Start	40
Warm Starts	40
Restarting JES2 after an Orderly Shutdown	47
Restarting JES2 after a System Failure	48
Specifying Job Journaling to Ease Restart Processing	48
Modifying JES2 Initialization Statement Specifications	48
How to Correct Initialization Errors	49

Poly-JES	50
Defining a Secondary JES2 Member to MVS	51
Starting an Alternate JES2 Subsystem as a Primary Subsystem	53
How to Initialize JES2 in a Multi-Access Spool Configuration	54
Accessing JES2 Spool Information in a MAS	56
Accessing JES2 Checkpoint Data Sets in a MAS	56
Initializing the Multi-Access Spool Configuration	56
Starting the Multi-Access Spool Configuration	58
Job Submission and Queuing	62
Output	64
RJE	64
TSO/E	64
Functional Subsystem Support	65
Functional Subsystem and Functional Subsystem Interface	65
Using Functional Subsystems in a Poly-JES Environment	66
Functional Subsystem Recovery Procedures	67

Part 2. Controlling JES2 Processes 69

Chapter 2. Controlling JES2 Processes	73
Devices	73
Defining Device Configuration	73
Assigning Devices Dynamically After Initialization	73
Remote Line and Device Configuration	74
Directing Responses to Display Commands	76
Job Submission	76
Internal Reader Facility	76
Card Readers	80
Network Jobs	80
Conversion	83
Pre-Conversion JCL Scan	84
JCL Conversion	84
Scanning the JOB Statement Accounting Field	84
Network Accounting	84
Converter Parameters	85
Defining a Job's Procedure Library	85
Job Selection and Execution	85
The JES2 Job Queue	86
Job Class	86
Job Scheduling Priority	88
Member Affinity	90
Job Scheduling Environment	90
Duplicate Job Name Control	91
Held Jobs	91
Setting Job Class Limits for Execution	91
Enabling Job Execution Selection	91
Controlling Job Execution Through Exits	91
Controlling the Sequence of Job Execution	92
JES2 Control of Batch Job Initiation	93
WLM Control of Batch Job Initiation	97
The Initiator Cataloged Procedure	99
System Resource Manager Control of the Batch Job Workload	99
Job Monitoring	100
Entering Commands from a Job Stream	101
Execution Batch Monitoring (XBM) Facility	101
Output	103

Default Data Set Characteristics	104
Output Priority.	104
Output Priority Aging	106
Output Processing	107
Considerations for Output Produced by APPC Transaction Programs	112
Output Class Assignment.	113
Setup Characteristics	114
Demand Setup and Output Data Set Grouping	115
Spin Data Set Processing	115
Spin Data Sets in the NJE Environment	115
System Data Set Characteristics	116
Specifying JES2 Output Size Limits	116
Variable Work Selection Criteria	116
Output Disposition for SYSOUT Data Sets	124
Dividing Output into Smaller Units	128
Defining Output Limits.	129
JES2-Provided Client Print Services	131
Printers and Punches	131
Print Chain Alias for 1403 and 3211 Printers	131
3211 Indexing	132
Defining the Advanced Function Printer (Using the PRT(nnnn) Statement)	132
Defining a Functional Subsystem for Advanced Function Printing (Using the FSS(accccccc) Statement)	133
Using Advanced Function Printing Printers	134
Creating Output for a 3540 Diskette Writer	135
The JES2 Print Separator	135
Creating a JESNEWS Data Set	137
JES2 System Data Sets	139
The JES2 Punch Separator Card.	141
Output Routing	142
How JES2 Resolves Destinations from Node to Node	147
Altering Destination Processing Through DESTDEF	152
External Writers	157
Held Job and Data Set Considerations.	157
Improving JES2 Processing.	159

Part 3. Spool Volume Configuration, Control, and Performance 161

Chapter 3. Spool Volume Configuration, Control, and Performance	163
Spool Configuration.	163
The SYS1.HASPACE Data Set	163
Defining Spool Space	165
Spool Allocation	166
Controlling Spool Space	166
Defining the Allocation IOT	167
Defining the Track Group Maps	168
Spool Partitioning	168
Dynamic Addition and Deletion of Spool Volumes.	171
Recovering from Spool Volume Failure	174
Spool Performance Considerations	175
Selecting Spool Devices	175
Allocation of Spool Space	176
Track Celling	177
Spool Offload Facility	178
Overview	178
Defining the Offload Facility.	179

SMF Record Summary: Transmitting and Receiving Jobs and SYSOUT	181
Offloading All Pre-Execution Jobs and SYSOUT	182
Reloading All Pre-Execution Jobs and SYSOUT	186
Offloading Selected Jobs and SYSOUT	188
Reloading Selected Jobs and SYSOUT	190
Using the Spool Offload Facility for Networking	192

Part 4. Checkpoint Data Set Definition and Configuration 193

Chapter 4. Checkpoint Data Set Definition and Configuration	195
JES2 Checkpoint Function	195
Placement of the Checkpoint Data Set.	196
Checkpoint Data Set Specifications	197
CKPTn Data Set Definition and Placement on a Coupling Facility	198
CKPTn Data Set Definition and Placement on DASD	199
Determining the Size of Your Checkpoint Data Set	201
Determining the Current Checkpoint Size.	201
Determining the New Checkpoint Size	201
Allow Room for Dynamic Checkpoint Expansion	202
Step 1: Calculating 4K Records	202
Step 2: Calculating the Checkpoint Size	204
Placing a Checkpoint on a Coupling Facility for the First Time	207
Correcting a Structure Error of Size	207
Correcting a Structure Error of Incorrect Attributes	208
The Checkpoint Cycle	208
Checkpoint Cycle Overview	209
Phase I - Checkpoint RESERVE, Lock, and Read	210
Phase II - Updating the Checkpoint	211
Phase III - Final Checkpoint Write and Data Set Release	211
Phase IV - Other Member Access	212
Checkpoint Configuration Modes	212
DUPLEX-Mode Processing (With Backup)	212
DUPLEX-Mode Processing (Without Backup)	216
DUAL-Mode Processing	217
Accessing the CKPTn Data Set in a MAS	221
Controlled Checkpoint Data Set Access	221
Member-Specific Parameter Recommendations	222
Contention-Driven Checkpoint Data Set Access	223
Replacement Data Set (NEWCKPTn) Definition	223
Space Allocation for NEWCKPTn Data Sets.	223
Placement of the NEWCKPTn Data Sets	225
Using the NEWCKPTn Data Sets	225
Checkpoint Reconfiguration, An Overview	228
Checkpoint Reconfiguration Concepts	229
Preparing for Checkpoint Reconfiguration.	229
Using the Checkpoint Reconfiguration Dialog	230
JES2-initiated Entrance into the Dialog	233
Operator-initiated Entrance into a Checkpoint Reconfiguration Dialog	238
Checkpoint Reconfiguration Recovery	240
Clean-up After a Checkpoint Reconfiguration	241
Moving a JES2 Checkpoint to a Coupling Facility Using System Managed Rebuild	244
Recovering from Member Failures on Other JES2 Members.	245
Checkpoint on DASD	245
Checkpoint on Coupling Facility Structure	245
Using Operator Commands	246

Using the AUTOEMEM Option.	248
Enabling the JES2 AUTOEMEM Option at Initialization.	251
Providing Copies of the JES2 Checkpoint to Application Programs	252
Using Versions= to Provide Copies of the Checkpoint Data Set for Use by Applications.	253

Part 5. Network Job Entry (NJE) 255

Chapter 5. Network Job Entry (NJE)	257
Overview of NJE	257
BSC Versus SNA	257
Logical and Physical Configurations.	258
Hardware Considerations for NJE	258
Data Flow Through a Network	259
How JES2 Processes Jobs from TSO/E User ID in NJE	260
Designing the Network	264
General Considerations	264
Network Topology	265
Performance Considerations	268
Security Considerations	269
Initializing the Network Job Entry Functions	270
Initialization Statements	270
Naming the Nodes in a Network	271
Using Destination Identifiers (DESTIDs)	273
Defining a Minimum Configuration for BSC NJE	274
Default NJE Parameters (BSC and SNA).	275
Using Different Operating Systems in a Network	279
Defining a Minimum Configuration for SNA NJE	281
Special Considerations for SNA NJE Networking	283
VTAM Definitions for SNA NJE	285
Displaying Information About a Network	287
Displaying NJE Global Parameters	288
Displaying Node Attributes	288
Displaying JES2 Applications for SNA NJE	288
Display Symbolic Destination Identifiers	288
Displaying Active Paths in a Network	289
Displaying NJE Connections	289
Sending a Display Command	290
Connecting the Network	290
Starting BSC Dynamic Connections.	291
Starting SNA Dynamic Connections.	291
SMF Record Summary: NJE (Network Job Entry) Processing	291
The Path Manager	291
Private Connections	294
Static Connections	295
Defining and Communicating Between Subnets	299
Determining Path Resistance	301
Path Selection Considerations.	305
Extending Network Capability	306
Adding a Node to an Existing Network.	309
Multi-Access Spool Configuration Considerations for NJE.	309
Example of a Multi-Access Spool Node	310
Queueing Messages to a Multi-Access Spool Node	311
Defining a Multi-Access Spool Node (SNA Considerations)	312

Part 6. Remote Job Entry 315

Chapter 6. Remote Job Entry (RJE)	317
Defining RJE Workstations to JES2	318
Planning for RJE Workstation System Growth	319
Defining RJE Devices	320
Modifying RJE Workstations	321
Recovering RJE Workstations from Failed Members.	321
SNA RJE Considerations.	322
VTAM LU and PU Parameters that Affect SNA RJE	322
VTAM APPL Definitions for SNA RJE	322
SNA RJE Buffer Size	323
BSC RJE Processing	323
BSC Multileaving Workstations Supported by JES2	324
BSC Teleprocessing Buffer Considerations	324
SMF Record Summary: RJE Processing	325
Defining Lines for RJE Workstations	325
Nondedicated Lines.	326
Dedicated Lines	326
Defining BSC Lines for RJE Workstations	327
Defining SNA Lines for RJE Workstations	329
RJE Line Passwords	329
Changing an RJE Workstation from BSC to SNA	329
Changing an RJE Workstation from SNA to BSC	329
Using Compaction on SNA RJE Workstations	330
How Compaction Works	330
Starting and Stopping Remote Job Entry	331
Options for Disconnecting Remote Lines	331
BSC Workstations	331
SNA RJE Workstations	332
JES2 RJE Bind Image.	336
Setting Line Density for RJE Devices	337
Altering the Sequence of Operations from an RJE Workstation	337
Pooling RJE Workstations	338
Expanding RJE Workstations	338
Consolidating RJE Workstations	338
Using CONDEST= to Specify the RJE Operator Console	339
Remote Message Spooling	340

Part 7. Providing Security for JES2 341

Chapter 7. Providing Security for JES2	343
Security Authorization Facility (SAF) of MVS	344
Using RACF to Provide Security	344
JES2 Access to Resources	344
Securing Resources	344
SMF Record Summary: RACF Security	347
Defining and Grouping Your Installation's Support Personnel	347
Specifying Access Authority.	348
Security Labels	348
Controlling Access to Data Sets JES2 Uses.	349
Controlling Input to Your System	349
Authorizing Networking Jobs and SYSOUT (NJE).	353
Controlling Access to Data that Resides on Spool	359
Controlling Where Output Can Be Processed	363

Authorizing the Use of Operator Commands	364
Using JES2 to Provide Security	372
JES2 Initialization Statements	372
JES2 Security Exit Points	374
Multiple Levels of a Security Product in a MAS	375

Part 8. Appendixes 377

Appendix A. IBM Devices Supported by JES2 and How to Use Them	379
DASD Utilization Tables	379

Appendix B. Miscellaneous JES2 Facilities	383
Automatic Command Processing	383
Writing a Day's Work Scheduler	383
Limiting Considerations	385
Using the MVS Message Service (MMS) for JES2 Messages	385
Managing Storage in JES2	385
Storage Considerations	386
Job Journaling, SMF Records, and SMF Exits	387
Spool Utilization	387
JES2 Spool Data Set Browse	387
Allocation	388
Using the Compatibility Interface	390
Using the ACB/RPL Interface	390
End of File Processing	392
Performance	393
Secondary Subsystem Support	393

Appendix C. The External Writer	395
Overview of the IBM-Supplied External Writer	395
Characteristics of the IBM-Supplied External Writer	395
How to Set Up and Start the External Writer	396
The External Writer Cataloged Procedure	396
How the IBM-Supplied Output Writer Routine Works.	399
Functions of the Output Writer Routine	400
How to Add Your Own Output Writing Routine	403
Replacing the IBM-Supplied Routine	403
Using Your Routine for Only Certain Jobs	403

Appendix D. Notices	411
Programming Interface Information	412
Trademarks.	412

Glossary	415
---------------------------	-----

Index	429
------------------------	-----

Figures

1. Example of a JES2 Initialization Data Set	17
2. HASPLIST Data Set Example Produced by Specifying the LIST Start Option	20
3. Example of a Two-Member Shared JES2 Configuration	55
4. Reassigning Member Identifiers to Different Processors	62
5. Representation of the Relationship between Functional Subsystem Components	66
6. Submitting a Job to the Internal Reader	77
7. The RDR Procedure	78
8. Specifying Procedure Libraries in the JES2 Procedure	85
9. Example of the Interaction of Priority-Aging Parameters, PRTYHIGH=, PRTYLOW=, and PRTYRATE= on JOBDEF Statement	97
10. IBM-Supplied INIT Procedure	99
11. Entering Commands from a Job Stream	101
12. Contents of the Example ORDPROC Member	103
13. Specifying the Procedure on the JOBCCLASS(v) Statement	103
14. Example JCL to Invoke ORDERIT	103
15. Example of the Interaction of Priority-Aging Parameters PRTYHIGH, PRTYLOW, and PRYORATE on OUTDEF Statement	107
16. The OUTDisp= Parameter	125
17. Example of OUTDisp as a Work Selection Criteria	127
18. Sample Initialization Stream Definitions	130
19. Sample JCL with Output Limits	130
20. Sample JES2 Print Separator Page	136
21. Sample JES2 Job Log	140
22. Using Destids to Route Output to a Printer at Another Node	144
23. Destids When Printer Moved to Node 2	145
24. Moving Printers without Notifying Other Nodes	145
25. Sample JES2 DESTID(jxxxxxxx) Initialization Values on Three Nodes	151
26. JES2 DESTID(jxxxxxxx) Initialization Values that Loop	151
27. DESTID(jxxxxxxx) and DESTDEF Initialization Stream Definitions	155
28. Multiple Destids that Match Output Routed to Special Local 5	156
29. Remote Pooling with RDEST=USER	157
30. Example of Defining and Allocating the JES2 SYS1.HASPACE Data Set	165
31. Allocation IOT and Minimum Storage Requirements	167
32. Display of Offload Devices	183
33. Offload Initialization Statements and \$\$ OFFLOADn,TYPE=TRANSMIT Relation	185
34. Offload Initialization Statements and \$\$ OFFLOADn,TYPE=RECEIVE	187
35. Offloading Data to Send to Another Node	192
36. Example of Defining Checkpoint Data Set	200
37. Estimated Structure Sizes for JES2 Checkpoint on a Coupling Facility	206
38. The Checkpoint Cycle (In a 3-Member Multi-Access Spool Environment)	209
39. Checkpoint Data Set Processing, DUPLEX Mode, Two-Member Multi-Access Spool Configuration - JESA Cycle	214
40. Checkpoint Data Set Processing, DUPLEX Mode, Two-Member Multi-Access Spool Configuration - JESB Cycle	215
41. Checkpoint Data Set Processing, DUAL Mode, Two-Member Multi-Access Spool Configuration	218
42. Checkpoint Data Set Processing -- DUAL Mode -- Three-Member Multi-Access Spool Configuration	220
43. Example of Checkpoint Data Set Forwarding	227
44. Two-Member MAS with JES2 Failure (Checkpoint on DASD)	247
45. Two-Member MAS with JES2 Failure (Checkpoint on Coupling Facility)	247
46. Two-Member MAS with JES2 and MVS Failure (DASD)	248
47. Sysplex with the AUTOEMEM Option Enabled, a JES2 Failure (DASD)	249
48. Sysplex with the AUTOEMEM Option Enabled, a JES2 Failure (Coupling Facility)	250

49.	Sysplex with the AUTOEMEM Option Enabled, an MVS System Failure	251
50.	The JES2 AUTOEMEM Option in a Two-Member Sysplex Configuration	252
51.	Simple SNA NJE Configuration	258
52.	Processing Flow Through a Network	262
53.	Basic Network Configurations.	266
54.	Gateway Configuration	267
55.	Backbone Network Configuration	268
56.	Defining Nodes Using Generics	272
57.	JES2 NJE Sign-On Password Verification	273
58.	NJE Sign-On Password Verification for Mixed Levels of JES2	273
59.	Minimum NJE Configuration (BSC only)	275
60.	Basic SNA Configurations	282
61.	Minimum NJE Configuration (SNA).	283
62.	Parallel SNA NJE Sessions Between Two Nodes	284
63.	Valid SNA Request Unit Sizes (Between 512 and 32512)	286
64.	Using Multiple SNA Log Mode Table Entries	287
65.	Sign-On Between Two Nodes Using Non-Path Manager Protocol	293
66.	Two Path Manager Nodes Sign-on Protocol	293
67.	Two Private Nodes Across Subnets	294
68.	Static Connections.	296
69.	Three-Node Network Configuration CONNECT Statements to Avoid Looping	298
70.	CONNECT Statements that Avoid Looping in 3-Node Network.	298
71.	Example of Defining Subnets	299
72.	Example of Subnets Defined in the Initialization Data Set	300
73.	Formula for Calculating the Resistance of Adjacent Nodes.	302
74.	Path Resistance Values	303
75.	An Expanded Network	308
76.	Multi-Access Spool Configuration (BSC).	310
77.	Multi-Access Spool Configuration (SNA).	313
78.	Using Remote Pooling to Accommodate an Expanding Workload	338
79.	Using Remote Pooling to Consolidate Resources	339
80.	General Flow of IBM's Output Writing Routine	402

Tables

1. JES2 Sample Initialization Data Sets	5
2. JES2 Initialization Statements	6
3. JES2 Initialization Control Statements	14
4. The Basic JES2 Procedure	24
5. The 'JESBACK' Back-up Procedure	25
6. Example of an Updated JES2 Procedure	25
7. JES2 Start Options	29
8. Subsystem Support Modules	32
9. Placement of Load Modules Based on LOADmod(jxxxxxxx) STORAGE= Specification	34
10. SMF Records Used When JES2 Starts or Stops a Member	39
11. Warm Start Types	43
12. Modification Heading	48
13. Multi-Access Spool and Checkpoint Data Set Compatibility	57
14. Priority Table Example	89
15. JES2 Commands Useful in Controlling the Batch Job Workload	94
16. Priority Calculation Default Values	105
17. Relationship of SYSOUT Specification to Number of Job Output Elements	108
18. Interrelationship Between the Four Factors Affecting Output Grouping	110
19. SMF Records Containing Job Output Information	111
20. Example of Six Output Groups on Output Queues	117
21. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue	118
22. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue	119
23. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue	119
24. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue	119
25. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue	119
26. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue	119
27. Example of Output Groups on Output Queues	121
28. Search Results When Specifying CLASS	121
29. Search Results When Specifying CLASS before ROUTECDE	123
30. Search Results When Specifying PRIORITY	123
31. JES2 Defaults for the OUTDISP Parameter	125
32. Assigned Alias Names for the 1403 and 3211 Printer Chains	131
33. Summary of Data Type and Printer Mode Compatibility	135
34. JES2 System Data Sets	140
35. Alphabetic Character Conversion to Digits for JES2 Punch Separator Cards	141
36. How JES2 Resolves Destinations with Symbolic Route Codes	146
37. How JES2 Resolves Destinations with Symbolic Route Codes	147
38. How JES2 Resolves Destinations -- Example 1	148
39. How JES2 Resolves Destinations -- Example 2	148
40. How JES2 Resolves Destinations -- Example 3	149
41. How JES2 Resolves Destinations -- Example 4	149
42. How JES2 Resolves Destinations -- Example 5	150
43. How JES2 Resolves Destinations from DESTDEF Initialization Statements	155
44. Maximum Spool LRECLs	166
45. Spool Volume Status Types and Definitions	171
46. Summary of Spool Volume Status Characteristics	172
47. SMF Records Used by JES2 Spool Offload Facility	181

48.	WS Criteria for Spool Offload Devices	189
49.	MOD Criteria for Spool Offload Receiving Devices	191
50.	JES2 Parameters Affecting Checkpoint Size	202
51.	JES2 Parameters Affecting Checkpoint Size	202
52.	Total 4K Records for the JES2 Checkpoint	203
53.	Sample Checkpoint Size Calculation	203
54.	Number of 4K Records per Track and Cylinder for Various DASD Devices	204
55.	Example of Defining and Allocating DASD JES2 Checkpoint Data Sets	205
56.	JES2 Initialization Statements that Define a Network	270
57.	Confusing JES2 Node Naming Conventions To Avoid.. . . .	271
58.	VTAM APPL Statement Parameters Necessary for a JES2 Connection	285
59.	SMF Records Used by JES2 NJE	291
60.	NODE(nnnn) Statement - PATHMGR= and PRIVATE= Parameter Specifications	295
61.	CONNECT Statement	296
62.	Resistance Calculation for Adjacent Connections	301
63.	Resistance Determination for Non-Adjacent Connections.	304
64.	JES2 Initialization Statements and Commands Used to Define a Network	318
65.	VTAM Parameters that Affect JES2	322
66.	VTAM APPL Statement Parameters Necessary for a JES2 Connection	322
67.	SMF Records Used by JES2 RJE	325
68.	Variable Statements Used to Alter the JES2 RJE Bind Image	336
69.	JES2 Resources and Associated RACF Classes.	345
70.	SMF Records Used by JES2 with RACF Security	347
71.	Device Names to Use for RACF Profiles.	352
72.	NODE Class Keywords and the UACC Meaning for Inbound Jobs	355
73.	NODES Class Keywords, UACC, and SYSOUT Ownership when Execution Node is Not Defined to &RACLNDE	357
74.	RACF Command Authority Hierarchy	365
75.	JES2 Commands with Profile Names and Minimum Required Authority	366
76.	JES2 Security-Related Initialization Statements	373
77.	Security-Related Exits	374
78.	Calculated Values for Several DASDs.	380
79.	Selected Device and BUFSIZE Parameter (on SPOOLDEF) Values and Resultant Utilization Percentages	380
80.	External Writer Parameter List	400
81.	Separator Routine Parameter List	407
82.	Block Character Routine Parameter List	409

About This Book

This book describes the general functions of JES2 and provides information describing JES2 initialization, JES2 processing, network job entry (NJE), remote job entry (RJE) for JES2, and factors affecting performance.

This book provides the information that you need to:

- Initialize JES2
- Tune JES2

This book is for installations running the JES2 element of z/OS. This book's companion book, *z/OS JES2 Initialization and Tuning Reference*, describes JES2 initialization statements and their parameters and provides summary charts that highlight details of the statements.

Who Should Use This Book

This book is intended for JES2 system programmers or for anyone responsible for initializing or tuning JES2. Installation procedures are release specific; therefore, they are provided in the Program Directory distributed with a specific product.

How to Use This Book

Use this book in conjunction with *z/OS JES2 Initialization and Tuning Reference*.

Most referenced publications are abbreviated throughout the text; their full titles appear in "Where to Find More Information" on page xv, which follows. Additionally, be aware of how this book uses references to 3800 printers.

3800 Printer

Unless specifically noted, all references to 3800 printers refer to the 3800-1, 3800-3, 3800-6 (that is, the 3800 models 1, 3, and 6).

Where to Find More Information

This book references the following publications for further details about specific topics. Abbreviated forms of these titles are used throughout this book. The following table lists all abbreviated titles, full titles, and their order numbers that are not listed in the z/OS Information Roadmap. Refer to that book for all z/OS publications.

Short Title Used in This Book	Title	Order Number
<i>NJE Installation</i>	<i>NJE Installation, Operation, and Use with JES2 and Other Systems</i>	GG22-9339
	<i>ES/9000 and ES/3090 PR/SM Planning Guide</i>	GA22-7123
	<i>IBM 3704 and 3705 Communications Controllers</i>	GC30-3008
	<i>IBM 3725 Model 1 Communications Controller</i>	GA33-0010

Short Title Used in This Book	Title	Order Number
	<i>System/370 Special Feature: Channel-to-Channel Adapter</i>	GA22-6893
	<i>OS/VS2 IBM 3540 Programmer's Reference</i>	GC24-5111
	<i>Advanced Function Presentation: Printer Information</i>	G544-3290
<i>DFP Advanced Services</i>	<i>DFSMS/MVS DFSMSdfp Advanced Services</i>	SC26-4921
	<i>z/OS DFSMS Macro Instructions for Data Sets</i>	SC26-4913
	<i>z/OS Communications Server: SNA Resource Definition Reference</i>	SC31-8778
	<i>OS/390 IBM Communications Server: SNA Programming</i>	SC31-8573

Using LookAt to look up message explanations

LookAt is an online facility that allows you to look up explanations for z/OS messages and system abends.

Using LookAt to find information is faster than a conventional search because LookAt goes directly to the explanation.

LookAt can be accessed from the Internet or from a TSO command line.

You can use LookAt on the Internet at:

www.ibm.com/servers/eserver/zseries/zos/bkserv/lookat/lookat.html

To use LookAt as a TSO command, LookAt must be installed on your host system. You can obtain the LookAt code for TSO from the LookAt Web site by clicking on **News and Help** or from the *z/OS Collection*, SK3T-4269.

To find a message explanation from a TSO command line, simply enter: **lookat** *message-id* as in the following example:

```
lookat iec192i
```

This results in direct access to the message explanation for message IEC192I.

To find a message explanation from the LookAt Web site, simply enter the message ID. You can select the release if needed.

Note: Some messages have information in more than one book. For example, IEC192I has routing and descriptor codes listed in *z/OS MVS Routing and Descriptor Codes*. For such messages, LookAt prompts you to choose which book to open.

Additional Information

Additional information about z/OS elements can be found in the following books.

Title	Order Number	Description
<i>z/OS Introduction and Release Guide</i>	GA22-7502	Describes the contents and benefits of z/OS as well as the planned packaging and delivery of this new product.
<i>z/OS Planning for Installation</i>	GA22-7504	Contains information that lets users: <ul style="list-style-type: none">• Understand the content of z/OS• Plan to get z/OS up and running• Install the code• Take the appropriate migration actions• Test the z/OS system
<i>z/OS Information Roadmap</i>	SA22-7500	Describes the information associated with z/OS including z/OS books and books for the participating elements.
<i>z/OS Summary of Message Changes</i>	SA22-7505	Describes the changes to messages for individual elements of z/OS. Note: This book is provided in softcopy only on the message bookshelf of the z/OS collection kit.

Part 1. JES2 Initialization

Chapter 1. JES2 Initialization	3
Installation Overview	3
Service Considerations	3
JES2 Initialization Process Overview	3
Modifying How JES2 Performs Initialization	4
JES2 Sample Initialization Data Sets	5
Initialization Statements and Parameters	6
Defining JES2 to the Cross-System Coupling Facility (XCF)	9
How JES2 Determines the JES2 XCF Group Name	9
XCF Group Name Restrictions	10
How JES2 Determines the JES2 XCF Group Member Name	10
Defining JES2 Structures in a CFRM Policy	11
How to Control JES2 Initialization	11
Creating an Initialization Data Set	12
JES2 Initialization Statements	12
Specifying JES2 Command and Message Prefixes	13
JES2 Initialization Control Statements	14
The JES2 Patching Facility	15
JES2 Operator Commands	16
Sample JES2 Initialization Data Set and HASPLIST Corrections	16
Creating the JES2 Cataloged Procedure	23
Specifying a Back-up JES2 Cataloged Procedure	25
Specifying User PROCLIBs in the JES2 Cataloged Procedure	25
Defining the Data Set for JES2 Initialization Parameters	26
Specifying the Start Options	27
Starting Using a JCL Procedure	27
Starting Using the Console	28
Controlling Initialization Using JES2 Exits and the \$SCAN Facility	32
Controlling JES2 Load Modules	32
JES2 Load Modules	32
Loading JES2 Subsystem Support Modules	33
JES2 Subsystem Module Placement and Storage Considerations	34
Controlling the Loading of Installation-Defined Load Modules	34
Starting and Stopping JES2	35
JES2 Program Properties	35
Starting JES2 for the First Time (A Cold Start)	36
JES2 Console Messages During Initialization	36
Performing an Orderly Shutdown of a JES2 Member	38
Running With Disabled JES2 Processors	38
SMF Record Summary: Starting and Stopping JES2	39
Using Event Notification Signalling with JES2	40
Restarting JES2	40
Cold Start	40
Warm Starts	40
All-Member Warm Start	41
Single-Member Warm Start	41
Quick Start	41
Hot Start	42
\$E MEM Command Start	42
Warm Start Considerations	43
Hot Start Considerations	46
Restarting JES2 after an Orderly Shutdown	47
Restarting JES2 after a System Failure	48

Specifying Job Journaling to Ease Restart Processing	48
Modifying JES2 Initialization Statement Specifications	48
How to Correct Initialization Errors.	49
Poly-JES	50
Defining a Secondary JES2 Member to MVS.	51
Installing a JES2 Secondary Subsystem	51
Starting an Alternate JES2 Subsystem as a Primary Subsystem.	53
How to Initialize JES2 in a Multi-Access Spool Configuration	54
Accessing JES2 Spool Information in a MAS	56
Accessing JES2 Checkpoint Data Sets in a MAS	56
Initializing the Multi-Access Spool Configuration.	56
Starting the Multi-Access Spool Configuration	58
Job Submission and Queuing	62
Displaying or Updating a Job's Affinity	62
Scheduling Environment	63
Restarting Jobs.	63
Duplicate Job Names	63
Priority Aging	64
Output	64
RJE	64
TSO/E	64
Functional Subsystem Support	65
Functional Subsystem and Functional Subsystem Interface	65
Using Functional Subsystems in a Poly-JES Environment	66
Functional Subsystem Recovery Procedures	67

Chapter 1. JES2 Initialization

JES2 initialization is the series of operations performed each time JES2 is started, in order to ready itself for processing.

Installation Overview

The following steps should be followed to ensure correct JES2 operation on an MVS system:

1. Become thoroughly familiar with the System Modification Program/E(SMP/E) before attempting to install JES2. (Refer to *z/OS SMP/E User's Guide* for information concerning this procedure.)
2. Install JES2 using the System Modification Program/E (SMP/E) on an existing MVS system, as outlined in the Program Directory that is distributed with the component package. (The program directory and component package should be retained for future reference.)
3. Define the JES2 spool data sets (generally named SYS1.HASPACE) and the checkpoint data set(s) (generally named SYS1.JESCKPT1 and SYS1.JESCKPT2 when they reside on DASD, or SYS1_JESCKPT1 and SYS1_JESCKPT2 when they reside on a coupling facility structure). (Refer to "Part 4. Checkpoint Data Set Definition and Configuration" on page 193 for further information concerning the specifications of these data sets.)
4. Define the JES2 initialization statements. (Refer to *z/OS JES2 Initialization and Tuning Reference* for full descriptions of these statements.)
5. Define a primary subsystem by specifying the PRIMARY keyword in the member IEFSSNxx in SYS1.PARMLIB. (Refer to *z/OS MVS Initialization and Tuning Reference* for a description of subsystem definition.)
6. Define the cataloged JCL procedure for JES2. (Refer to *z/OS MVS JCL User's Guide* for a description of cataloged procedures in general and *z/OS MVS Initialization and Tuning Reference* for a description of subsystem cataloged procedures in particular.)

Service Considerations

The System Modifications Program/E (SMP/E) is required to install all IBM*-provided changes to the JES2 element of z/OS. It is highly recommended that any user modifications (both system and distribution library) be made using SMP/E.

JES2 Initialization Process Overview

Each time you start a JES2 subsystem, MVS establishes JES2 as an authorized subsystem address space and gives control to JES2 to initialize itself through the following procedures:

- Begin the JES2 procedure through either an operator command (S JES2) or an IPL-time automatic process such as the COMMNDxx members of SYS1.PARMLIB. Then MVS:
 - locates the JES2 procedure in SYS1.PROCLIB.
 - allocates the libraries to which the DD statements in the JES2 procedure point, including those that the JES2 subsystem uses to locate the JES2 initialization statements.

- gives control to the JES2 subsystem, which establishes the JES2 general ESTAE protection before calling a series of initialization routines (IRs), as follows, to process each phase of JES2 initialization.
- Process the start options specified and call installation Exit 0, allowing the installation to perform pre-initialization processing.
- Process the current status of the subsystem interface (SSI), establishing necessary control blocks and preparing for later SSI requests.
- Allocate various control blocks required during all JES2 processing or temporarily during initialization processing.
- Process the initialization statements specified through parmlib, console, and exit routine input, and call installation Exit 19 for each initialization statement.
- Process the initialization statements specified, verifying the validity of the parameters and calculated variable parameters. These post-processing functions include:
 - General processing and verifying the complete set of initialization statements and their parameters (specified and defaulted)
 - Calculating variable parameters based on other parameter values
 - Validating the parameters specified and the associated control blocks.
- Allocate the control blocks required to:
 - Define the devices specified through the initialization statements
 - Allow I/O activity for the defined devices
- Process the initialization and perform validation, as required for JES2 network job entry (NJE) activity.
- Process the initialization and perform validation, as required for JES2 remote job entry (RJE) activity.
- Validates the current JES2 direct access devices (DASD) that are defined through the initialization statements, analyzes the spool volumes and the checkpoint data sets (whether they reside on DASD volumes or coupling facility structures), and performs any required related activities (such as checkpoint data set forwarding).
- Validates the multi-access spool (MAS) configuration specifications.
- Allocate common storage control blocks for command and message traffic, MVS initiator support, the subsystem interface (SSI), the JES2 trace facility, and other JES2-supported facilities.
- Connect the JES2 devices defined through the initialization statements to MVS device control blocks.
- Call miscellaneous MVS services (for example, to establish interfaces).
- Allocate the control blocks necessary to define those JES2 processors that are required immediately after initialization that cannot be dynamically added later.
- Generate the information string for the request subsystem (SSI) version call 54 routine.
- Complete JES2 initialization by building the required buffer pools and calling installation Exit 24 (post-initialization exit routines).

Modifying How JES2 Performs Initialization

The specific manner in which JES2 is initialized depends upon your choice of start options and initialization statements. You define how JES2 will perform initialization through the initialization options, which specify:

- Whether JES2 is to warm start or cold start.
- Whether JES2 should force the formatting of the spool volumes.

- The ddname for the DD statement in the JES2 cataloged procedure that defines the input data set(s) for the initialization statements.
- Whether JES2 should stop and give control to the operator for further statement input from the console after the parmlib input is exhausted.
- Which data set, as defined by the CKPT1= or CKPT2= parameter on the CKPTDEF statement, should be used to access JES2 warm-start information.
- Whether the checkpoint data set definitions should be reconfigured.
- Whether JES2 will print a log of the initialization statements specified and any related diagnostics to the data set referenced by the HASPLIST DD statement in the JES2 cataloged procedure.
- Whether JES2 will automatically start normal processing after initialization or wait for an operator command to start.
- Which start options will be overridden (by specifying the OPTSDEF initialization statement).

You define which JES2 functions and device defaults are to be overridden by specifying the initialization statements:

- Logical initiator characteristics
- Internal reader characteristics
- Local and remote device characteristics
- Default job and SYSOUT class characteristics
- NJE header and trailer buffers
- Multi-access spool (MAS) control statements
- Changes to certain JES2 default parameter values

You can control how JES2 schedules jobs by the way you specify these options and statements during JES2 initialization. Furthermore, you can respecify these options and statements to reflect changes in your system's configuration and workload any time JES2 is started.

Attention: Be aware, however, that some parameter changes require a JES2 cold start or all-member warm start and some parameters are ignored on a hot or warm start. These parameters are noted in the “Modification” heading for each parameter description in *z/OS JES2 Initialization and Tuning Reference*.

Carefully plan the initialization specification of each of these parameters to prevent having to revise them later through a warm start or cold start.

JES2 Sample Initialization Data Sets

IBM distributes the HASlxxxx members in the SYS1.SAMPLIB data set library that you can tailor to meet your installation's needs. To ensure that your SYS1.SAMPLIB is not overwritten, IBM recommends moving these data sets to an installation library before tailoring the HASlxxxx members. The following table lists these initialization data sets and their specific roles.

Table 1. JES2 Sample Initialization Data Sets

Member Name	Contents	Use
HASIPROC	Sample JCL procedure	Tailor, rename, and move to the production JCL procedure library for use as the JES2 subsystem JCL.
HASIPARM	Sample JES2 initialization parameter templates	Use to create production JES2 initialization parameters in other libraries.

Table 1. JES2 Sample Initialization Data Sets (continued)

Member Name	Contents	Use
HASIASM	Sample JCL procedure.	Use when assembling an IBM JES2 source module or an installation JES2 exit routine (it saves the resulting object code). This member can be tailored, placed in a production procedure library, and used when the SMP/E system installation and maintenance tool is not managing JES2 code.
HASIBLD	Sample job stream that uses the HASIASM procedure.	Assembles IBM JES2 source-distributed modules (including sample exit routines) and link edits each of the production load modules. This member can be tailored, placed in another procedure library, and used when the SMP/E system installation and maintenance tool is not managing JES2 code.
HASISMPA	Sample job stream.	Tailor, then use to force the SMP/E system installation and maintenance tool to reassemble all modules for the JES2 release it manages. This two-step procedure might be necessary to assemble all modules at an installation with the same level of MVS system macros.

Initialization Statements and Parameters

This section explains how to specify the JES2 initialization statements and parameters and how JES2 performs initialization under different conditions.

Throughout this book, an initialization statement refers to a JES2 specification that can contain further parameter specifications. For example, PRINTDEF is a statement; LINECT, DBLBUFR, and UCS are parameters on that statement. Most initialization statements contain a set of parameters that relate to a single JES2 function. For example, the SPOOLDEF statement contains several parameters used to define the JES2 spool volume environment. Some statements, however, contain no parameters (for example, DEBUG: this statement is either specified as DEBUG=YES or DEBUG=NO).

Table 2 provides an alphabetical list of the JES2 initialization statements and briefly describes the function of each. It is intended as a reference to help you decide which statements and parameters to use to initialize your JES2 member. *z/OS JES2 Initialization and Tuning Reference* describes each of these statements in detail and specifies their functions, formats, and default values.

Table 2. JES2 Initialization Statements

Initialization Statement	Function
APPL(avvvvvvv)	Defines a SNA NJE application to JES2.
BADTRACK	Specifies an address or range of addresses of defective spool volume tracks JES2 is not to use.

Table 2. JES2 Initialization Statements (continued)

Initialization Statement	Function
BUFDEF	Defines the local JES2 buffers to be created.
CKPTDEF	Defines the JES2 checkpoint data set(s) and the checkpointing mode.
CKPTSPACE	Defines how much additional space is available for expanding the JES2 checkpoint record.
COMPACT	Defines a compaction table for use in remote terminal communications.
CONDEF	Defines the JES2 console communication environment.
CONNECT	Specifies a static connection between the nodes identified.
DEBUG	Specifies whether debugging information is to be gathered by JES2 during its operation for use in testing.
DESTDEF	Defines how JES2 processing interprets and displays both job and SYSOUT destinations.
DESTID(jxxxxxxx)	Defines a destination name (mostly for end-user use as on a JCL statement) for a remote terminal, another NJE node or a local device.
D MODULE(jxxxxxxx)	Displays diagnostic information for specified JES2 assembly modules and installation exit assembly modules.
ESTBYTE	Specifies, in thousands of bytes, the default estimated output (SYSOUT) for a job at which the "BYTES EXCEEDED" message is issued, and the subsequent action taken.
ESTIME	Specifies, in minutes, the default elapsed estimated execution time for a job, the interval at which the "TIME EXCEEDED" message is issued, and whether the elapsed time job monitor feature is supported.
ESTLNCT	Specifies, in thousands of lines, the default estimated print line output for a job, the interval at which the "LINES EXCEEDED" message is issued, and the subsequent action taken.
ESTPAGE	Specifies the default estimated page output (in logical pages) for a job, the interval at which the "PAGES EXCEEDED" message is issued, and the subsequent action taken.
ESTPUN	Specifies, in number of cards, the default estimated punch card output for a job, the interval at which the "CARDS EXCEEDED" message is issued, and the subsequent action taken.
EXIT(nnn)	Associates the exit points defined in JES2 with installation exit routines.
FSS(accccccc)	Specifies the functional subsystem for printers that are supported by an FSS (for example Print Services Facility).
INIT(nnn)	Specifies the characteristics of a JES2 logical initiator.
INITDEF	Specifies the number of JES2 logical initiators to be defined.
INTRDR	Specifies the characteristics of all JES2 internal readers.
JOBCLASS(v)	Specifies the characteristics associated with job classes, started tasks, and time sharing users.
JOBDEF	Specifies the characteristics that are assigned to jobs that enter the JES2 member.
JOBPRTY(n)	Specifies the relationship between job scheduling priorities and job execution time.

Table 2. JES2 Initialization Statements (continued)

Initialization Statement	Function
LINE(nnnn)	Specifies the characteristics of one teleprocessing line or logical line (for SNA) to be used during remote job entry or network job entry.
L(nnnn).JT(m)	Specifies the characteristics for a job transmitter on an NJE line.
L(nnnn).ST(m)	Specifies the characteristics for a SYSOUT transmitter on a line defined for network job entry.
LOADMOD(jxxxxxxx)	Specifies the name of a load module of installation exit routines to be loaded.
LOGON(n)	Identifies JES2 as an application program to VTAM*.
MASDEF	Defines the JES2 multi-access spool configuration.
MEMBER(n)	Defines the members of a JES2 multi-access spool configuration.
NAME	Specifies the module or control section to be modified through subsequent VER and REP initialization statements.
NETACCT	Specifies a network account number and an associated local account number.
NJEDEF	Defines the network job entry characteristics of this JES2 node.
NODE(nnnn)	Specifies the characteristics of the node to be defined.
OFF(n).JR	Specifies the characteristics of the offload job receiver associated with an individual offload device.
OFF(n).JT	Specifies the characteristics of the offload job transmitter associated with an individual offload device.
OFF(n).SR	Specifies the characteristics of the offload SYSOUT receiver associated with an individual offload device.
OFF(n).ST	Specifies the characteristics of the offload SYSOUT transmitter associated with an individual offload device.
OFFLOAD(n)	Specifies the characteristics of the logical offload device.
OPTSDEF	Defines the options that are currently in effect.
OUTCLASS(v)	Specifies the SYSOUT class characteristics for one or all output classes.
OUTDEF	Defines the job output characteristics of the JES2 member.
OUTPRTY(n)	Defines the association between the job output scheduling priorities and the quantity (records or pages) of output.
PCDEF	Specifies the definition for various JES2 processes.
PRINTDEF	Defines the JES2 print environment.
PRT(nnnn)	Specifies the characteristics of a local printer.
PUNCHDEF	Defines the JES2 punch environment.
PUN(nn)	Specifies the characteristics of a local card punch.
R(nnnn).PR(m)	Specifies the characteristics of a remote printer.
R(nnnn).PU(m)	Specifies the characteristics of a remote punch.
R(nnnn).RD(m)	Specifies the characteristics of a remote card reader.
RDR(nn)	Specifies the characteristics of a local card reader.
RECVOPTS(type)	Specifies the error rate below which the operator will not be involved in the recovery process.

Table 2. JES2 Initialization Statements (continued)

Initialization Statement	Function
REDIRect(vvvvvvvv)	Specifies where JES2 directs the response to certain display commands entered at a console.
REP	Specifies replacement patches for JES2 modules during initialization.
RMT(nnnn)	Specifies the characteristics of a BSC or SNA remote terminal.
SMFDEF	Specifies the system management facilities (SMF) buffers to JES2.
SPOOLDEF	Defines the JES2 spool environment.
SSI(nnn)	Specifies the characteristics associated with individual subsystem interface definitions.
SUBTDEF	Specifies the number of general purpose subtasks you wish JES2 to attach during initialization.
TPDEF	Defines the JES2 teleprocessing environment.
TRACE(n)	Specifies whether a specific trace ID(s) is to be started.
TRACEDEF	Defines the JES2 trace environment.
VER	Specifies verification of replacement patches for JES2 modules during initialization.

Defining JES2 to the Cross-System Coupling Facility (XCF)

JES2 uses the JES common coupling services (JES XCF) for communicating JES2 member status and other data among the JES2 XCF group members in a multi-access spool (MAS) configuration. Optionally, you can modify this communication mechanism through the JES common coupling services. Refer to *z/OS MVS Programming: JES Common Coupling Services* for a description of the JES common coupling services (JES XCF macros and exits).

All members of a MAS need to be contained within the same sysplex. If your installation is running a single MVS system, you can specify PLEXCFG=XCFLOCAL on the IEASYSxx parmlib member to avoid the need for formatting a sysplex couple data set. Also, you need to ensure that there is enough space on the sysplex couple data set to accommodate the JES2 XCF group and its member names.

How JES2 Determines the JES2 XCF Group Name

To allow the JES2 XCF group members to know about each other, either:

- Accept the JES2 defaults
- or
- Define the members to JES2 through the initialization data set.

XCF needs to know about the groups that use its services. It knows about these groups through their XCF group name. The JES2 XCF group name allows a JES2 MAS to be known to XCF. Define each member to JES2 by assigning each MAS a group name that is unique within its sysplex. This group name defaults to the JES2 local node name, which is defined by the NAME= parameter on the NODE(nnnn) initialization statement. (Note that if you use the JES2 network job entry (NJE) facility, this NAME= parameter matches the OWNNODE= parameter on the NJEDEF statement.)

If you need to refer to the sysplex by the same name, specify the same name on the SYSPLEX= keyword in the COUPLExx member of SYS1.PARMLIB. For example, the sysplex specified below is named POK:

SYSPLEX=POK

This is the IBM recommended approach. It reduces system complexity by allowing the sysplex name, the node name, and the JES2 XCF group to share the same name.

You can assign a unique name through the XCFGRPNAME= parameter on the MASDEF initialization statement if your:

- NAME= parameter on the NODE(nnnn) statement conflicts with an existing XCF group name.
- Current node name does not meet naming restrictions for a JES2 XCF group name
- Sysplex contains more than one MAS.

While IBM does not recommend more than one JES2 MAS in a sysplex, your installation can choose this approach. To avoid the ABEND that results if multiple MAS names default to an XCF group name of N1, all but one MAS member must specify a nodename for the OWNNAME= parameter on their NJEDEF statements.

JES2 determines the XCF group name for your JES2 MAS in the following order:

1. XCFGRPNAME= keyword on the MASDEF initialization statement, if specified:
MASDEF ...XCFGRPNAME=POK
2. The node name defined by the NAME= parameter on the NODE(nnnn) initialization statement, if specified:
NODE(nnnn) NAME=POK
3. The node name defined by the nnnn subscript of the NODE(nnnn) initialization statement, if specified:
NODE(POK)
4. N1, the JES2-assigned default node name if a node name or XCFGRPNAME= is not specified in the initialization data set.

XCF Group Name Restrictions

When coding the XCF group name on the XCFGRPNAME parameter of the MASDEF statement, the name should follow the XCF naming conventions.

If the XCF group name is not coded on the MASDEF statement, the nodename on the NODE(xxxxxxx) initialization statement should follow the XCF naming conventions.

Note: To avoid using the names IBM uses for its XCF groups, do not begin group names with the letters A through I or the character string SYS. Also, do not use the name UNDESIG, which is reserved for use by the system programmer in your installation.

How JES2 Determines the JES2 XCF Group Member Name

Within a group, each JES2 member is assigned an XCF member name. The member name that identifies a JES2 member to the JES2 XCF group is composed of the NAME= parameter on the NODE(nnnn) statement, the \$ symbol, and the OWNMEMB= parameter on the MASDEF initialization statement. For example, using the following initialization statements:

```
NODE(1) NAME=POKX
MEMBER(1) NAME=HAS1
MASDEF OWNMEMB=HAS1
```

the member name for MVS is **POKX\$HAS1**.

For information about how to specify NAME= on the MEMBER(n) initialization statement and OWNMEMB= on the MASDEF initialization statement, see “Starting the Multi-Access Spool Configuration” on page 58.

Because the member name includes a \$, you might want to avoid using it on the OWNMEMB= parameter and NAME= parameter of the NODE(nnnn) initialization statement to eliminate potential confusion.

The JES2 XCF member names must be unique within the JES2 XCF group.

Defining JES2 Structures in a CFRM Policy

To specify that a checkpoint data set resides on a coupling facility structure, you must have taken the following steps when planning your JES2 configuration.

1. Format a coupling facility resource management (CFRM) couple data set for use at your installation. See *z/OS MVS Setting Up a Sysplex* for specific instructions on defining the coupling facility resource management administrative policies. These policies each provide a number of coupling facilities with structures that can contain checkpoint data sets. Since JES2 supports system managed processes, you should also review the section “System-Managed Processes Considerations” in *z/OS MVS Setting Up a Sysplex* to enable system managed functions. We recommend that structure full monitoring be suppressed by setting a FULLTHRESHOLD value of 0 for the coupling facility structure where a checkpoint is to reside.

2. Ensure that you have allocated enough storage for the:

- Coupling facilityStructure
- JES2 checkpoint data set

(To determine these sizes, see “Determining the Size of Your Checkpoint Data Set” on page 201.)

3. Prior to starting the JES2 address space, specify the coupling facility structure where a checkpoint is to reside on the CKPTDEF initialization statement as described in “Checkpoint Data Set Specifications” on page 197 and *z/OS JES2 Initialization and Tuning Reference*.

How to Control JES2 Initialization

This section discusses initialization and configuration features of JES2. Specific considerations unique to NJE are discussed in “Chapter 5. Network Job Entry (NJE)” on page 257.

JES2 initialization is performed after JES2 is started and before JES2 begins to process jobs. To control JES2 initialization:

1. Create a data set containing the initialization statements.

For a description of the different methods for specifying an initialization data set, see:

- “JES2 Initialization Statements” on page 12.
- “Specifying JES2 Command and Message Prefixes” on page 13.

- “The JES2 Patching Facility” on page 15.
 - “JES2 Operator Commands” on page 16.
2. Select initialization statements to be entered at the console during JES2 initialization.
For more information, see “JES2 Initialization Control Statements” on page 14.
 3. Update the JES2 procedure to include definitions of the initialization data set(s).
For more information, see “Creating the JES2 Cataloged Procedure” on page 23.
 4. Select start options to be used during JES2 initialization.
For more information, see “Specifying the Start Options” on page 27.
 5. Use the exit and scanning facilities to modify initialization processing and thus modifying or supplementing JES2 functions.
For more information, see “Controlling Initialization Using JES2 Exits and the \$SCAN Facility” on page 32.

Creating an Initialization Data Set

An initialization data set contains the initialization statements and, optionally, JES2 control statements, operator commands, and patching facility and AMASPZAP control statements. A sample initialization data set -- `SYS1.VnRnMn.SHASSAMP(HASIPARM)` -- contains templates that you can modify for a particular installation. Before modifying the sample data set, see “Defining the Data Set for JES2 Initialization Parameters” on page 26.

You can mix the operator commands and the patching facility, AMASPZAP, and initialization control statements among the initialization statements without any special coding requirements. Figure 1 on page 17 shows an example of an initialization data set that contains operator commands and initialization control statements.

The initialization data set should be protected to prevent disclosing passwords contained on initialization statements, such as `NODE`, `LINE`, `LOGON`, and `RMT` statements. If a security product is used, ensure that no one can access the data set. If an installation uses RACF, specifying `UACC=NONE` for the data set provides this protection.

JES2 Initialization Statements

The initialization statements allow installations to specify the functions and device characteristics JES2 will use during its current execution. You must define most devices (local and remote) through JES2 initialization statements; however, some can be defined dynamically through `$ADD` operator commands.

If you do not add these statements to the initialization stream, JES2 will not define them; no default values are provided. JES2 counts the devices you have thus defined, and based on these individual device statements, is able to provide default values for various other initialization parameters. These defaults are noted in the descriptions of the parameters thus affected in *z/OS JES2 Initialization and Tuning Reference*. If you choose not to specify initialization statements for many of the other available JES2 functions, default values are provided.

Use the `SMFDEF` initialization statement to define the system management facilities (SMF) buffers that JES2 requires for SMF to collect and record MVS system and job-related information. The `BUFNUM=` parameter specifies the number of buffers JES2 obtains. If your installation has 3800 printers, this number should be

calculated by the formula presented with the description of the SMFDEF statement in *z/OS JES2 Initialization and Tuning Reference*.

JES2 can evaluate whether or not a particular SMF record should be written, by use of a routine in JES2 installation Exit 21. See *z/OS JES2 Installation Exits* for information about Exit 21.

Specifying JES2 Command and Message Prefixes

The CONCHAR= parameter on the CONDEF initialization statement specifies the prefix:

- For all JES2-issued messages
- By which JES2 identifies commands destined for the particular member of a multi-access spool (MAS).

Normally, JES2-initiated messages are tagged with a “\$” at the beginning of the text. However, the “\$” character is taken from the value of CONCHAR=; therefore, a different specification of this value for each member allows the origin of the message to be uniquely identified.

You can determine whether the CONCHAR= value applies only to the MVS system on which the JES2 member is running, or to all MVS systems in the sysplex through the SCOPE= parameter on the CONDEF initialization statement.

If you specify CONDEF ...,SCOPE=SYSTEM...., the CONCHAR value is recognized on this MVS system alone. In order to issue a JES2 command that is to take effect on a specific JES2 member, an installation would have to direct the command to that system through one of the following:

- The MVS ROUTE command
- or
- A sysplex-scope command prefix (such as the system name, if the installation uses IEECMDPF SAMPLIB member).

If each member of a MAS specifies CONDEF ...,SCOPE=SYSTEM,...., and the same value for the CONCHAR= parameter, then a ROUTE *ALL command can be used to make global changes to parameters on all members in that MAS. Because the MVS ROUTE *ALL command provides a single-system image for all JES2 members and MVS systems in the sysplex, the SCOPE=SYSTEM specification would be more valuable for a large MAS. However, with a single console displaying output from multiple MVS and JES2 images, it might be difficult to determine which member issued a message.

To identify the member that originated a command or message, you would have to notice the MVS system ID (**SYS1**) on each console display in response to a command:

```
SYS1          $d condef
               $HASP830 CONDEF 942
$HASP830 CONDEF AUTOCMD=20,CONCHAR=$,BUFNUM=200,CMDNUM=100,
$HASP830          BUFFREE=200,BUFWARN=80,MASMSG=200,RDIRAREA=Z,
$HASP830          RDRCHAR=$,SCOPE=SYSTEM,DISPLEN=64,DISPMAX=100
```

If you specify CONDEF ...,SCOPE=SYSPLEX.... on each member of a MAS, the CONCHAR= value is recognized as belonging to this JES2 member, no matter on which MVS system in the sysplex the command entered. The SCOPE=SYSPLEX specification might be valuable for a smaller MAS, where the CONCHAR value for

each member can be remembered easily. Note that the JES2 limit of 22 CONCHAR= values indicates that a MAS of more than 22 members could not use this scheme.

If you use this method, you cannot enter the MVS ROUTE *ALL command to send messages to each member. SCOPE=SYSPLEX implies that JES2 still provides a multisystem image to installations.

JES2 Initialization Control Statements

JES2 initialization control statements can be used to control the listing and entry of initialization statements while JES2 processes the initialization stream. Initialization control statements do not set JES2 processing values. Table 3 lists the JES2-supported control statements.

Table 3. JES2 Initialization Control Statements

Statement	Explanation
LIST=NO	Ends the listing of statements on devices defined by the HASPLIST DD card. LIST=NO remains in effect until a LIST=YES statement is encountered.
LOG=YES*	Copies the current and subsequent initialization statements to the HARDCPY console. Logging remains in effect until a LOG=NO statement is encountered.
<u>LOG=NO</u>	Ends the logging of initialization statements. LOG=NO is automatically in effect initially and remains in effect until a LOG=YES statement is encountered.
/*	Designates the beginning of a comment. Comments can appear anywhere a blank can be coded, except within vectors or subscripts. The comment is listed or logged as appropriate but is otherwise ignored.
*/	Designates the end of a comment. Comments can appear anywhere a blank can be coded, except within vectors or subscripts. The comment is listed or logged as appropriate but is otherwise ignored.
DISPLAY D	<p>Displays the value of specified JES2 initialization statements or specific parameters on those statements. All parameter values are displayed unless specific parameters are listed. You can add multiple statements to one DISPLAY statement; use commas between statement names. (Refer to the syntax below.)</p> <p>Your message can also be displayed by following the command with message text enclosed in single quotes as the following example shows.</p> <div style="border: 1px solid black; padding: 5px; margin: 10px 0;"> <pre>&{DISPLAY&} 'message text',stmt-name=(parm1,...parmn), &{D &} stmt-name=(parm1...)</pre> </div> <p>Note: Place the DISPLAY statement following the initialization statement that you need to display in order for JES2 to read these statements prior to building the “DISPLAY” response.</p>

Table 3. JES2 Initialization Control Statements (continued)

Statement	Explanation
CONSOLE	<p>Causes JES2 to get subsequent initialization parameter statements from the operator through the system console. The operator's reply to the message issued as a result of the CONSOLE statement can be any valid statement. JES2 remains in console mode until the operator replies END in response to the \$HASP469 (REPLY PARAMETER STATEMENT, CANCEL, OR END) message. Optionally, the operator can reply CANCEL in response to the \$HASP469 message to end JES2 initialization.</p> <p>Two methods of adding additional initialization statements to the JES2 initialization data set are available to the operator through use of the CONSOLE option. The first method can be used only if the JES2 initialization data set initially includes the CONSOLE control statement. This causes JES2 to enter console mode at the time the CONSOLE statement is read. At this time the operator can add or override additional initialization statements.</p> <p>The second method is to use the CONSOLE option to stop JES2 initialization processing after all initialization statements have been read and processed prior to any subsequent initialization processing. The operator is permitted to add additional statements at this time. Consistent with JES2 initialization, if JES2 reads more than one initialization statement for a particular parameter, the last value read is used. This allows the operator either to add new statements to the initialization deck or to change any statements previously entered.</p>
*	<p>These statements are also controlled by options specified at the time you start JES2. You will only produce output if the start options, LIST and LOG, are specified. To display the current start options, use the DISPLAY OPTSDEF command (during JES2 initialization) and then override the options (using the OPTSDEF statement) from the console, if necessary. See <i>z/OS JES2 Initialization and Tuning Reference</i> for more information.</p>

The JES2 Patching Facility

Patch and AMASPZAP statements can be used to make minor and temporary modifications to the JES2 object code until JES2 is restarted by directly replacing the changed code. The JES2 Patching Facility changes only the memory copy of data; the copy residing on DASD (for example, LPA) cannot be replaced.

The JES2 patching facility makes temporary patches to any module in JES2 (HASJES20 or installation exit load module) or to any absolute storage address in the address space into which JES2 is loaded. Because these patches are valid only until a module is reloaded, they must be applied every time that JES2 is started.

JES2 reloads the load modules at different stages in processing:

- Subsystem support modules are reloaded during all starts except a hot start.
- HASJES20 is reloaded in response to a JES2 START command any time the member is started.

These patches are applied at the time JES2 is initialized. The patching facility statements are submitted to the JES2 initialization data set.

There are two basic patching formats:

1. Using the NAME initialization statement to specify the module name

2. Specifying the module name in the VER initialization statement.

Note: If you specify the module name in both the NAME and the VER initialization statement, JES2 cannot patch the data.

For more directions on how to code the patch statements, see the NAME, REP, and VER initialization statements in *z/OS JES2 Initialization and Tuning Reference*. Directions for using the AMASPZAP program are provided in the "SPZAP" topic in *z/OS MVS Diagnosis: Tools and Service Aids*. --> JES2 processes the patch and AMASPZAP statements as they are read.

JES2 Operator Commands

The operator can use JES2 operator commands to control the initial status of devices. For instance, operator commands can be used to start RJE lines during initialization. (RJE lines, unlike other devices, cannot be started automatically by an initialization statement.) Or the operator can issue MVS system commands, such as those to vary devices online and offline, before JES2 starts processing. JES2 operator commands are described in *z/OS JES2 Commands*.

During initialization, JES2 stores the operator commands in temporary message buffers. Then, when initialization is complete, JES2 processes the commands. To ensure that operator commands are completely processed before JES2 starts processing jobs, you should use the REQ start option, which lets the operator start JES2 processing. Alternatively, the \$\$ command can be included as the last operator command in the initialization data set, eliminating the need for operator intervention.

Sample JES2 Initialization Data Set and HASPLIST Corrections

The following two figures provide examples of the JES2 initialization data set used to start JES2 and the HASPLIST data set that results from processing the initialization data set. The HASPLIST data set is generated through the LIST=YES parameter on the OPTSDEF initialization statement. Note that when an error occurs, the operator must retype the entire initialization statement correctly and follow it with an end statement to continue initialization processing.

You can preallocate a data set and indicate to JES2 to use it for HASPLIST. In this case, you need to perform the preallocation with DCB parameters of LRECL=121 and RECFM=FBA. You need to ensure that the BLKSIZE on the preallocated data set is an integer multiple of LRECL; otherwise an **013** abend occurs.

```

OPTSDEF LIST=YES
/*****
/*
/*          SAMPLE JES2 PARAMETER LIBRARY LISTING          */
/*
*****/
CKPTDEF CKPT1=(DSN=SYS1.JESCKPT1,VOL=CHECK1,INUSE=YES),
        CKPT2=(DSN=SYS1.JESCKPT2,VOL=CHECK2,INUSE=YES),
        MODE=DUPLEX,DUPLEX=ON
/*****
/*
/*          LOCAL DEVICES          */
/*
*****/
RDR(1) UNIT=00C
RDR(2) UNIT=011,PRIOLIM=9,CLASS=X,AUTH=(JOB=NO,SYSTEM=NO,DEVICE=NO),
      PRDEST=R3
PRT(1) UNIT=002,CLASS=AJH,UCS=PN
PRT(2) UNIT=00E,CLASS=AJH,UCS=PN
PRT(3) UNIT=00F,CLASS=A,ROUTECD=22,UCS=PN
PRT(4) UNIT=018,CLASS=NI,MARK=YES,BURST=NO,TRKCELL=YES
PUN(1) UNIT=00D,PAUSE=YES
INTRDR PRIOLIM=9,AUTH=(JOB=NO,SYSTEM=NO,DEVICE=NO)
INITDEF PARTNUM=8
INIT(1) CLASS=AFJKE /*INITIATOR 1*/
INIT(2) CLASS=BCDEF /*INITIATOR 2*/
INIT(3) CLASS=DEFGH /*INITIATOR 3*/
INIT(4) CLASS=XKH /*INITIATOR 4*/
INIT(5) CLASS=JKEBF /*INITIATOR 5*/
INIT(6) DRAIN /*SPARE INITIATOR*/
INIT(7) DRAIN /*SPARE INITIATOR*/
INIT(8) DRAIN /*SPARE INITIATOR*/
JOBCLASS(STC) LOG=NO,OUTPUT=NO,CONDPURG=YES /*STARTED TASK DEFINITIONS*/
JOBCLASS(TSU) REGION=50K,COMMAND=IGNORE,MSGLEVEL=(1,1),CONDPURG=YES
JOBCLASS(S) PROCLIB=03,HOLD=YES /*SYSTEM PROGRAMMER CLASS */
OUTCLASS(H) OUTDISP=(HOLD,HOLD),TRKCEL=NO /*SYSOUT CLASS HELD */
/*FOR OUTPUT */
OUTCLASS(N) TRKCELL=YES
OUTCLASS(X) OUTPUT=DUMMY,TRKCELL=NO /*THROWAWAY CLASS*/

```

Figure 1. Example of a JES2 Initialization Data Set (Part 1 of 3)

```

/*****
/*
/*          NJE/RJE INITIALIZATION PARAMETERS          */
/*
/*****
NJEDEF      OWNNODE=1,NODENUM=10,LINENUM=15,RESTNODE=10
LINE(1)     UNIT=040,DUPLEX=FULL,TRANSPAR=YES,REST=10
LINE(2)     UNIT=041,TRANSPAR=YES,PASSWORD=SECRET,REST=20
LINE(3)     UNIT=042,TRANSPAR=YES,PASSWORD=SECRET,REST=15
LINE(4)     UNIT=043,TRANSPAR=YES,PASSWORD=SECRET,REST=50
LINE(5)     UNIT=044,TRANSPAR=YES,PASSWORD=SECRET,REST=10
LINE(6)     UNIT=SNA
LINE(7)     UNIT=SNA,PASSWORD=LINE4PW
RMT(1)      DEVTYP=3780,LINE=1,NUMPUN=1,TRANSPAR=YES,BUFEXPEN=1,
            COMPRESS=YES
R1.PR1      PRWIDTH=144
RMT(2)      DEVTYP=2922,NUMPU=1,CONS=YES,MULTILV=YES,TRANSPAR=YES
R2.PR1      PRWIDTH=132
RMT(3)      DEVTYP=S/370,NUMPRT=2,CONS=YES,MULTILV=YES,TRANSPAR=YES
R3.PR1      PRWIDTH=150,FCBLOAD=YES
R3.PR2      PRWIDTH=132
RMT(4)      DEVTYP=1130,CONS=YES,MULTILV=YES,NUMPUN=1
R4.PU1      START=NO
RMT(5)      DEVTYP=SYSTEM/3,NUMRDR=3,NUMPUN=2,CONS=YES,MULTILV=YES
R5.PR1      PRWIDTH=132
RMT(6)      DEVTYP=2780,NUMPUN=1,TRANSPAR=YES,MRF2780=YES,HTABS=YES
R6.PR1      PRWIDTH=144
RMT(7)      DEVTYP=LUTYPE1,ROUTECD=10,BUFSIZE=512,DISCINTV=8000,
            NUMPUN=1,COMPRESS=YES
RMT(8)      DEVTYP=LUTYPE1,LINE=6,BUFSIZE=256,NUMPUN=1
OPTSDEF LIST=NO
/*****
/*
/*          REMOTE PASSWORDS          */
/*
/*****
RMT(1)      PASSWORD=CHICAGO
RMT(2)      PASSWORD=BOARDWLK
RMT(3)      PASSWORD=ALBANY
RMT(4)      PASSWORD=LACKLSTR
RMT(5)      PASSWORD=KALAMAZO
RMT(6)      PASSWORD=UNIQUE
OPTSDEF LIST=YES

```

Figure 1. Example of a JES2 Initialization Data Set (Part 2 of 3)

```

/*****
/*
/*          JES2 PARAMETER OVERRIDES          */
/*
/*****
BUFDEF    BELOWBUF=(LIMIT=10),EXTBUF=(LIMIT=30)
SPOOLDEF  TRKCELL=6
PRINTDEF  NIUCS=GF12
/*****
/*
/*          MULTI-ACCESS SPOOL CONFIGURATION PARAMETERS          */
/*
/*****
MASDEF    OWNMEMB=SYSA,SHARED=NOCHECK
MEMBER(1) NAME=SYSA
MEMBER(2) NAME=SYSB
D SPOOLDEF VOLUME
D CKPTDEF CKPT1          /* DISPLAY CURRENT */
D CONDEF CONCHAR          /* PARAMETER VALUES */
/*****
/*
/*          OPERATOR OVERRIDES          */
/*
/*****
CONSOLE          /* ALLOW OPERATOR TO OVERRIDE */
/*****
/*
/*          EVENT TRACE OPTIONS          */
/*
/*****
TRACEDEF    ACTIVE=YES,          /* START EVENT TRACING */
              LOG=(CLASS=A,SIZE=200,START=YES), /* LOG TRACE OUTPUT */
              PAGES=4,TABLES=20,TABWARN=50 /* SET TABLE SIZE/NUMBER */
TRACE(1-*) START=YES          /* START ALL TRACE IDS) */
/*****
/*
/*          OPERATOR COMMANDS          */
/*
/*****
$S LINE(1-5)
$TLINE(1),TR=YES          /*TRACE I/O COMPLETIONS ON LINE 1*/
$VS,'V (234,235,236,237),OFFLINE'
/*****
/*
/*          END OF JES2 PARAMETER LIBRARY LISTING          */
/*
/*****

```

Figure 1. Example of a JES2 Initialization Data Set (Part 3 of 3)

JES2 PARAMETER LIBRARY LISTING
CORRECTING INITIALIZATION PARAMETER ERRORS
PAGE 1

```

SHASPARM STMT 1 OPTSDEF LIST=YES
SHASPARM STMT 2 /*****
SHASPARM STMT 3 /* */
SHASPARM STMT 4 /* SAMPLE JES2 PARAMETER LIBRARY LISTING */
SHASPARM STMT 5 /* */
SHASPARM STMT 6 /*****
SHASPARM STMT 7 CKPTDEF CKPT1=(DSN=SYS1.JESCKPT1,VOL=CHECK1,INUSE=YES),
                      CKPT2=(DSN=SYS1.JESCKPT2,VOL=CHECK2,INUSE=YES),
                      MODE=DUPLEX,DUPLEX=ON
SHASPARM STMT 8 /*****
SHASPARM STMT 9 /* */
SHASPARM STMT 10 /* LOCAL DEVICES */
SHASPARM STMT 11 /* */
SHASPARM STMT 12 /*****
SHASPARM STMT 13 RDR(1) UNIT=00C
SHASPARM STMT 14 RDR(2) UNIT=011,PRIOLIM=9,CLASS=X,
                      AUTH=JOB=NO,SYSTEM=NO),PRTDEST=3
SHASPARM STMT 15 PRT(1) UNIT=002,CLASS=AJH,UCS=PN
SHASPARM STMT 16 PRT(2) UNIT=00E,CLASS=AJH,UCS=PN
SHASPARM STMT 17 PRT(3) UNIT=00F,CLASS=A,ROUTECD=22,UCS=PN
DIAGNOSTIC STMT 17 RC=(18),PRT(3) ROUTECDE (ELEMENT 1) - INVALID ROUTE
DIAGNOSTIC STMT 17 CODE
CONSOLE STMT 18 PRT(3) UNIT=00F,CLASS=A,ROUTECD=R22,UCS=PN
CONSOLE STMT 19
                      END
SHASPARM STMT 20 PRT(4) UNIT=018,CLASS=NI,MARK=YES,BURST=NO,TRKCELL=YES
SHASPARM STMT 21 PUN(1) UNIT=00D,PAUSE=YES
SHASPARM STMT 22 INTRDR PRIOLIM=9,AUTH=(JOB=NO,SYSTEM=NO,DEVICE=NO)
DIAGNOSTIC STMT 22 RC=(03),INTRDR PRIOLIM - INVALID PARAMETER STATEMENT
CONSOLE STMT 23 INTRDR PRTYLIM=9,AUTH=(JOB=NO,SYSTEM=NO,DEVICE=NO)
CONSOLE STMT 24 END

```

Figure 2. HASPLIST Data Set Example Produced by Specifying the LIST Start Option (Part 1 of 4)

JES2 PARAMETER LIBRARY LISTING
PAGE 2

```

SHASPARM  STMT  25  INITDEF  PARTNUM=8
SHASPARM  STMT  26  INIT(1)  CLASS=AFJKE          /*INITIATOR 1  */
SHASPARM  STMT  27  INIT(2)  CLASS=BCDEF          /*INITIATOR 2  */
SHASPARM  STMT  28  INIT(3)  CLASS=DEFGH          /*INITIATOR 3  */
SHASPARM  STMT  29  INIT(4)  CLASS=XKH            /*INITIATOR 4  */
SHASPARM  STMT  30  INIT(5)  CLASS=JKEBF          /*INITIATOR 5  */
SHASPARM  STMT  31  INIT(6)  DRAIN                /*SPARE INITIATOR */
SHASPARM  STMT  32  INIT(7)  DRAIN                /*SPARE INITIATOR */
SHASPARM  STMT  33  INIT(8)  DRAIN                /*SPARE INITIATOR */
SHASPARM  STMT  34  JOBCCLASS(STC) LOG=NO,OUTPUT=NO, /*STARTED TASK  */
                      CONDPURG=YES                /*DEFINITIONS   */
SHASPARM  STMT  35  JOBCCLASS(TSU) REGION=50K,COMMAND=IGNORE, /*TIME-SHARING */
                      MSGLEVEL=(1,1),CONDPURG=YES          /*USER DEFINITIONS */
SHASPARM  STMT  36  JOBCCLASS(S) PROCLIB=03,HOLD=YES        /*SYSTEM PROGRAMMER*/
                      /*CLASS                          */
SHASPARM  STMT  37  OUTCLASS(H) OUTDISP=(HOLD,HOLD),        /*SYSOUT CLASS HELD*/
                      TRKCEL=NO                          /*FOR OUTPUT      */
DIAGNOSTIC STMT  37  RC=(03),OUTCLASS(H) TRKCEL - INVALID PARAMETER
DIAGNOSTIC STMT  37  STATEMENT
CONSOLE    STMT  38  OUTCLASS(H) OUTDISP=(HOLD,HOLD),TRKCELL=NO
CONSOLE    STMT  39  END
SHASPARM  STMT  40  OUTCLASS(N) TRKCELL=YES
SHASPARM  STMT  41  OUTCLASS(X) OUTPUT=DUMMY,TRKCELL=NO /*THROWAWAY CLASS */

```

Figure 2. HASPLIST Data Set Example Produced by Specifying the LIST Start Option (Part 2 of 4)

JES2 PARAMETER LIBRARY LISTING
PAGE 3

```

SHASPARM STMT 42 /*****/
SHASPARM STMT 43 /* */
SHASPARM STMT 44 /* NJE/RJE INITIALIZATION */
SHASPARM STMT 45 /* */
SHASPARM STMT 46 /*****/
SHASPARM STMT 47 NJEDEF OWNODE=1,NODENUM=10,LINENUM=15,RESTNODE=10
SHASPARM STMT 48 LINE(1) UNIT=040,DUPLEX=FULL,TRANSPAR=YES,REST=10
SHASPARM STMT 49 LINE(2) UNIT=041,TRANSPAR=YES,PASSWORD=SECRET,REST=20
SHASPARM STMT 50 LINE(3) UNIT=042,TRANSPAR=YES,PASSWORD=SECRET,REST=15
SHASPARM STMT 51 LINE(4) UNIT=043,TRANSPAR=YES,PASSWORD=SECRET,REST=50
SHASPARM STMT 52 LINE(5) UNIT=044,TRANSPAR=YES,PASSWORD=SECRET,REST=10
SHASPARM STMT 53 LINE(6) UNIT=SNA
SHASPARM STMT 54 LINE(7) UNIT=SNA,PASSWORD=LINE4PW
SHASPARM STMT 55 RMT(1) DEVTYPE=3780,LINE=1,NUMPUN=1,TRANSPAR=YES
SHASPARM STMT 56 BUFEXPEN=1,COMPRESS=YES
DIAGNOSTIC STMT 55 RC=(03),RMT(1) BUFEXPEN - INVALID PARAMETER STATEMENT
CONSOLE STMT 56 RMT(1) DEVTYPE=3780,LINE=1,NUMPUN=1,TRANSPAR=YES,
CONSOLE STMT 56 BUFEXPAN=1,COMPRESS=YES
CONSOLE STMT 57 END
SHASPARM STMT 58 R1.PR1 PRWIDTH=144
SHASPARM STMT 59 RMT(2) DEVTYPE=2922,NUMPU=1,CONS=YES,MULTILV=YES,
TRANSPAR=YES
SHASPARM STMT 60 R2.PR1 PRWIDTH=132
SHASPARM STMT 61 RMT(3) DEVTYPE=S/370,NUMPRT=2,CONS=YES,MULTILV=YES,
TRANSPAR=YES
SHASPARM STMT 62 R3.PR1 PRWIDTH=150,FCBLOAD=YES
SHASPARM STMT 63 R3.PR2 PRWIDTH=132
SHASPARM STMT 64 RMT(4) DEVTYPE=1130,CONS=YES,MULTILV=YES,NUMPUN=1
SHASPARM STMT 65 R4.PU1 START=NO
SHASPARM STMT 66 RMT(5) DEVTYPE=SYSTEM/3,NUMRDR=3,NUMPUN=2,CONS=YES,
MULTILV=YES
SHASPARM STMT 67 R5.PR1 PRWIDTH=132
SHASPARM STMT 68 RMT(6) DEVTYPE=2780,NUMPUN=1,TRANSPAR=YES,MRF2780=YES,
HTABS=YES
SHASPARM STMT 69 R6.PR1 PRWIDTH=144
SHASPARM STMT 70 RMT(7) DEVTYPE=LUTYPE1,ROUTECD=10,BUFSIZE=512
DISCINTV=8000,NUMPUN=1,COMPRESS=YES
SHASPARM STMT 71 RMT(8) DEVTYPE=LUTYPE1,LINE=6,BUFSIZE=256,NUMPUN=1
SHASPARM STMT 72 OPTSDEF LIST=NO
SHASPARM STMT 85 /*****/
SHASPARM STMT 86 /* */
SHASPARM STMT 87 /* JES2 PARAMETER OVERRIDES */
SHASPARM STMT 88 /* */
SHASPARM STMT 89 /*****/
SHASPARM STMT 90 BUFDEF BELOWBUF=(LIMIT=10),EXTBUF=(LIMIT=30)
SHASPARM STMT 91 SPOOLDEF TRKCELL=6
SHASPARM STMT 92 PRINTDEF NIUCS=GF12

```

Figure 2. HASPLIST Data Set Example Produced by Specifying the LIST Start Option (Part 3 of 4)

JES2 PARAMETER LIBRARY LISTING
PAGE 4

```

SHASPARM STMT 93 /*****
SHASPARM STMT 94 /* */
SHASPARM STMT 95 /* MULTI-ACCESS SPOOL CONFIGURATION PARAMETERS */
SHASPARM STMT 96 /* */
SHASPARM STMT 97 /*****
SHASPARM STMT 98 MASDEF OWNMEMB=SYSA,SHARED=NOCHECK
SHASPARM STMT 99 MEMBER(1) NAME=SYSA
SHASPARM STMT 100 MEMBER(2) NAME=SYSB
SHASPARM STMT 101 D SPOOLDEF VOLUME
SHASPARM STMT 102 D CKPTDEF CKPT1 /*DISPLAY CURRENT */
SHASPARM STMT 103 D CONDEF CONCHAR /*PARAMETER VALUES */
SHASPARM STMT 104 /*****
SHASPARM STMT 105 /* */
SHASPARM STMT 106 /* OPERATOR OVERRIDES */
SHASPARM STMT 107 /* */
SHASPARM STMT 108 /*****
SHASPARM STMT 109 CONSOLE /*ALLOW OPERATOR */
/*TO OVERRIDE VALUES*/

CONSOLE STMT 110 END
SHASPARM STMT 111 /*****
SHASPARM STMT 112 /* */
SHASPARM STMT 113 /* EVENT TRACE OPTIONS */
SHASPARM STMT 114 /* */
SHASPARM STMT 115 /*****
SHASPARM STMT 116 TRACEDEF ACTIVE=YES, /* START EVENT TRACING*/
LOG=(CLASS=A,SIZE=200,START=YES), /* LOG TRACE OUTPUT */
PAGES=4, TABLES=20,TABWARN=50 /* SET TABLE SIZE */
/* NUMBER */

SHASPARM STMT 117 TRACE(1-*) START=YES /* START ALL TRACE IDS */
SHASPARM STMT 118 /*****
SHASPARM STMT 119 /* */
SHASPARM STMT 120 /* OPERATOR COMMANDS */
SHASPARM STMT 121 /* */
SHASPARM STMT 122 /*****
SHASPARM STMT 123 $$ LINE(1-5)
SHASPARM STMT 124 $TLINE(1),TR=YES /*TRACE I/O */
/*COMPLETIONS ON LN1*/

SHASPARM STMT 125 $VS,'V (234,235,236,237),OFFLINE'
SHASPARM STMT 126 /*****
SHASPARM STMT 127 /* */
SHASPARM STMT 128 /* END OF JES2 PARAMETER LIBRARY LISTING */
SHASPARM STMT 129 /* */
SHASPARM STMT 130 /*****
SHASPARM STMT 131 /* THIS IS A NULL JES2 INITIALIZATION DATA SET

```

Figure 2. HASPLIST Data Set Example Produced by Specifying the LIST Start Option (Part 4 of 4)

Creating the JES2 Cataloged Procedure

To start the JES2 component, an installation must provide a subsystem cataloged JCL procedure (PROC). The PROC name can be a maximum of four characters. For other naming restrictions, see *z/OS MVS JCL User's Guide*. Prior to IPL, define the PROC in the IEFSSNxx member(s) of SYS1.PARMLIB.

Instead of a distributed JES2 procedure, IBM provides the sample member 'HASIPROC' in the SYS1.VnRnMn.SHASSAMP data set. 'HASIPROC' is a sample JCL procedure that should be tailored, renamed, and moved to the production JCL procedure library for use as the JES2 subsystem JCL (the procedure specified on a START command to start JES2).

The basic JES2 procedure (Table 4 on page 24) contains an EXEC statement and five data definition (DD) statements named PROC00, PROC01, HASPLIST, HASPPARM and STEPLIB. PROC00 defines a default procedure library to be used for converting the JCL of batch jobs, time-sharing logons, and system tasks. HASPLIST defines what is normally a dummy output data set, but you can modify this statement to permanently point to a specific device or data set. Also, you can use the START command facilities to generate a IEFORDER statement to override the HASPLIST statement.

The following parameters on the EXEC statement deserve mentioning:

PGM= Specify the name of the JES2 load module. (It must reside in an authorized library.)

TIME= Specify 'NOLIMIT' or 1440 to prevent system ABEND code 322 (CPU time limit exceeded).

REGION=

Do not code this (or specify REGION=0M) to prevent any virtual storage limitations being put on the JES2 address space.

PERFORM=

Specify a unique performance group for tracking JES2 resources through RMF.

PARM=

Specify 'Warm,NOREQ' for the start parameters in the JES2 procedure. If necessary you can override these parameter specifications on the 'S JES2' command. See "Specifying the Start Options" on page 27.

Table 4. The Basic JES2 Procedure

//JES2	PROC	N='SYS1.V2R4M0',L=SHASLINK,
//		M=JES2PARM,PN=SYS1,PL=PARMLIB,U=
//		PROC00='SYS1.PROCLIB',PROC01='SYS1.PROCLIB'
//IEFPROC	EXEC	PGM=HASJES20,TIME=1440,PARM=(WARM,NOREQ)
//HASPLIST	* DD	DDNAME=IEFORDER
//HASPPARM	DD	UNIT=&U,DSN=&PN;.&PL(&M),DISP=SHR
//PROC00	DD	DSN=&PROC00,DISP=SHR
//PROC01	DD	DSN=&PROC01,DISP=SHR
//STEPLIB	DD	DSN=&N;.&L,DISP=SHR

* The MVS message, IEC130I HASPLIST DD STATEMENT MISSING, will be issued if this DD name is not included here.

You can change the JES2 procedure by entering updates with a TSO/E editor such as SPF or the IBM IEBUPDTE utility program. You can add DD statements to the JES2 procedure to define:

- Other cataloged procedure libraries that are associated with job classes by the JOBCLASS initialization statement or by the /*JOBPARM JES2 control statement. Each library should be defined by a PROCnn DD statement. For instance, to specify a special library for TSO/E logons, code PROCLIB=nn (where nn corresponds to the associated PROCnn DD statement) in the JOBCLASS(TSU) initialization statement.
- One or more initialization data sets that define different conditions and types of workloads. See Table 6 on page 26 for an example of an updated JES2 procedure.

IBM recommends that installations specify DDNAMEs in the format of PARMxxxx when defining installation parameter libraries in the JES2 procedure. After initialization, JES2 automatically unallocates data sets that have a DDNAME of HASPLIST, HASPPARM, or PARMxxxx. By unallocating these data sets, installations can dynamically delete the devices on which these data sets reside.

Specifying a Back-up JES2 Cataloged Procedure

IBM recommends that you define a back-up JES2 cataloged procedure. If JES2 fails to start because of either a JCL or an allocation error, you can use this member to start JES2 while you resolve the errors with the original procedure.

You must build a member in one of the data sets defined by the IEFPSDI statement in the MSTRJCLxx. In the example below, the data set SYS1.PROCLIB contains the JCL found for the JESBACK member.

Enter the following command to start this procedure:

```
START JESBACK,JOBNAME=JES2,SUB=MSTR
```

where *JESBACK* is an installation-defined name for the member of SYS1.PROCLIB that contains the back-up JES2 procedure.

Table 5. The 'JESBACK' Back-up Procedure

//IEFPROC	EXEC PGM=HASJES20,TIME=1440,PARM=(WARM,NOREQ)
//HASPPARM	DD UNIT=3390,DSN=SYS1.SECOND,DISP=SHR
//PROC00	DD DSN=SYS1.PROCLIB,DISP=SHR

Once you have corrected the error in the original procedure, you can restart it by entering a \$P JES2,ABEND operator command to bring down the JES2 member. Then restart the JES2 member through the MVS START command (S JES2) once you have replaced the back-up procedure with the original JES2 procedure.

Specifying User PROCLIBs in the JES2 Cataloged Procedure

It is important to add your user PROCLIB statements using symbolic data set names that can be changed by the start command. Otherwise a missing user PROCLIB would require IPLing a backup system to make any changes to the production system.

To ensure performance and integrity, do not:

- Allocate additional extents or release extents
- Compress a PROCLIB data set
- Defragment (move) a volume containing a PROCLIB.

Table 6 on page 26 is a copy of the JES2 procedure that will allow an operator to change user PROCLIB data set names in the event of a failure. If a failure is experienced during JES2 startup because of a missing user PROCLIB, restart JES2 and supply the name of SYS1.PROCLIB for the missing user PROCLIB.

Table 6. Example of an Updated JES2 Procedure

```

/*****
/*
/*          EXAMPLE OF AN UPDATED JES2 PROCEDURE
/*
/*****
//JES2   PROC DSN1='SYS1.PROCLIB',      * STANDARD PROCLIB.      *
//       DSN2='SYS1.PROCLIB2',        * SYSTEM SUPPORT PROCS. *
//       DSN3='SYS1.PROCSPP',          * PROG. PRODUCT PROCS.  *
//       DSN4='SYS2.PROCLIB',          * USER PROCLIB.       *
//       STEPLIB='SYS1.JES2.SHASLINK', * JES2 PGM LIBRARY     *
//       PGN=20,                      * PERFORM FOR JES2      *
//       MBR=HASIPARM,TYPE=CTS         * DEFAULT NAME ALTERNATE *
//*                                     * PARM, TYPE (HAS/NJE/CTS) *
/*****
/* MODIFIED JES2 START PROCEDURE
/* CHANGES -
/* ADDITIONAL PROCLIBS - 1) SYS1.PROCLIB (SYSTEM PROCLIB)
/*                          2) SYS1.PROCLIB2 (SPECIAL PROCS)
/*                          3) SYS1.PROCSPP (P.P. PROCS)
/*                          4) SYS2.PROCLIB (USER PROC'S)
/* SELECT VERSION OF JES VIA TYPE=HAS/NJE/CTS
/* CHANGED TO USE SYS1.PROCLIB FOR JES2 INIT. PARMS
/* LAST CHANGE - 10/14/86.
/*
/*****
/*
//IEFPROC EXEC PGM=&TYPE.JES20,TIME=1440,
//          PERFORM=&PGN,          DUMMY PERFORM FOR TRACKING
//          PARM=(WARM,NOREQ) SPECIFY START OPTIONS
//STEPLIB DD DSN=&STEPLIB,DISP=SHR (MUST BE AUTHORIZED)
//*
//***** DEFAULT PROCEDURE LIBRARIES LIST *****
//*
//PROC00 DD DSN=&DSN1,DISP=SHR
//       DD DSN=&DSN2,DISP=SHR
//       DD DSN=&DSN3,DISP=SHR
//       DD DSN=&DSN4,DISP=SHR
//*
//***** INDIVIDUAL PROCXX CARDS FOR EACH PROCLIB. *****
//*
//PROC01 DD DSN=&DSN1,DISP=SHR   SPECIFIC DECLARATIONS
//PROC02 DD DSN=&DSN2,DISP=SHR   FOR USE WITH JOBPARM PROC=
//PROC03 DD DSN=&DSN3,DISP=SHR   PARAMETERS.
//PROC04 DD DSN=&DSN4,DISP=SHR   *
//HASPPARM DD DSN=SYS1.PROCLIB(&TYPE.PARM;),DISP=SHR
//PARMBACK DD DSN=SYS1.JESPARM(&MBR),DISP=SHR      /*ALTERNATE*/
//HASPLIST DD DDNAME=IEFRDER      /*LISTING */
//*

```

Note: Datasets specified in the JES2 procedure (i.e. all DD statments) must be referred to in one of the following ways:

- Cataloged in the master catalog or user catalog
- Specify UNIT= and VOL= on the JCL DD statement
- SMS managed data (do not specify UNIT or VOLUME) (UNIT= and VOL= on the JCL DD statement are ignored.)

Defining the Data Set for JES2 Initialization Parameters

The HASPPARM DD statement defines a member in SYS1.VnRnMn.SHASSAMP that initially contains the sample initialization data set. The sample initialization data set is **only** an example and requires system-specific modification. You will find it to be a useful base for coding your initialization data set(s).

When creating the JES2 initialization data set in an installation, you must move it from SYS1.VnRnMn.SHASSAMP to a data set comprised of 80 character records in a fixed record format. The data set can be blocked with a BLKSIZE that is a multiple of 80. If an installation's SYS1.VnRnMn.SHASPARM data set is not blocked, you can improve system performance by moving this member to a blocked library and tailoring the HASPPARM DD statement in the JES2 cataloged procedure accordingly.

Use the HASPPARM DD statement to define an initialization data set to replace the IBM-supplied null data set. You can also create the initialization data set separately and define it by its own DD statement in the procedure.

Installations can use resources more efficiently by concatenating data sets. If the DD statement points to separate files for the JES2 initialization parameters, you can

- Separate JES2 parameters according to function.
- Allow multiple programmers to manage distinct subsets of parameters.
- Share a subset of parameters between the members of a JES2 MAS.

For the members of a JES2 MAS to share parameters, some HASPPARM data sets must be shared among all the members.

The initialization of JES2 supports the concatenation of data sets of unlike attributes as the initialization statement data set. This allows the use of a card reader to introduce the statements to JES2 while they are being tested by the installation, by concatenating it to the standard PARMLIB initialization member.

Specifying the Start Options

When JES2 is started, it uses the start options specified to determine how it will perform the current initialization. The start options described in this section are defined by JES2. However, you can define other start options for your installation by using the scanning facility (a \$SCAN table is provided for initialization options) or an Exit 0 routine for this purpose. (Refer to *z/OS JES2 Installation Exits* for further information on these procedures.) Unless these options are specified in the JCL procedure used for automatic starting of JES2, you must specify the start options from the console.

Starting Using a JCL Procedure

When the options are specified on the JCL procedure (on the EXEC statement) or by specifying the PARM= parameter on the MVS START command, JES2 suppresses the \$HASP426 (SPECIFY OPTIONS) message and completes initialization without operator intervention unless CONSOLE initialization control statements have been added to the JES2 initialization data set or an initialization statement is in error. *z/OS MVS JCL Reference* gives these rules using the MVS START command. These rules govern the use of the PARM= parameter on the EXEC JCL statement and apply to how you specify JES2 start options with a JCL procedure. The examples below illustrate both correct and incorrect use of these rules in starting JES2.

```
S JES2,PARM=(FORMAT,SPPOOL=VALIDATE) ... is incorrect.
S JES2,PARM=(FORMAT,'SPPOOL=VALIDATE') ... is correct.
S JES2,PARM='FORMAT,SPPOOL=VALIDATE' ... is correct.
S JES2,PARM=(FORMAT,SPPOOL='VALIDATE') ... is incorrect.
```

Once the options are specified (from the JCL procedure or on the MVS START command), JES2 does some initial verification, then issues the \$HASP493 message indicating that initialization has started. After it has accepted the options, JES2 reads the specified initialization data set. Message \$HASP492 indicates that

initialization is complete. JES2 is then ready to start processing jobs. If the NOREQ options was specified, JES2 automatically starts processing. Otherwise, you will receive the following messages:

```
$HASP400 ENTER REQUESTS
```

This message requests the operator to use the \$S command to start JES2 processing. JES2 issues the \$HASP492 message to indicate whether initialization was performed for all members of the MAS configuration or only for the member indicated by **memname** (the member name). \$HASP492 also indicates the type of start performed to start member activity.

Starting Using the Console

If the PARM= parameter is not specified on the MVS START command for JES2 then you are choosing to start JES2 by specifying options from the console. JES2 issues message \$HASP426:

```
*id $HASP426 SPECIFY OPTIONS - JES jeslevel SSNAME=ssname
```

You should respond using the MVS REPLY command to specify the JES2 options determined by your installation procedures. (See *z/OS MVS System Commands* for a complete description of the REPLY command.)

```
REPLY id,options
```

For example, if the id for a reply is "003", the \$HASP426 message is:

```
003 $HASP426 SPECIFY OPTIONS..... message
```

You would reply as follows:

```
REPLY 003,options.....
```

Notes:

1. You only are allowed one line on the operator console to provide the JES2 options in your reply.
2. The reply to supply options must follow the rules for JES2 initialization statements.

The examples below illustrate correct responses:

```
REPLY 003,a,b,c,d,e
REPLY 003,'a,b,c,d,e'
REPLY 003,a,b,x=144,d,e
```

The option table that follows, Table 7, lists the JES2 start options and an explanation of each. If you respond to message \$HASP426 with the \$PJES2 command, JES2 will terminate.

If this is the first start of JES2, then the following sequence applies:

1. You should specify the COLD (or FORMAT) option. If COLD (or FORMAT) is not specified, JES2 issues the following messages:

```
$HASP479 UNABLE TO OBTAIN CKPT DATA SET LOCK - I/O ERROR
$HASP454 SHOULD JES2 BYPASS THE MULTI-MEMBER INTEGRITY LOCK?
(Y OR N)
```

Reply Y to message \$HASP454; JES2 will then issue:


```

$HASP478 INITIAL CHECKPOINT READ IS FROM CKPTn
      (dsname ON volser)
$HASP434 INVALID CHECKPOINT RECORD ON CKPTn DATASET
$HASP285 JES2 CHECKPOINT RECONFIGURATION IN PROGRESS
$HASP289 CKPT1 AND/OR CKPT2 SPECIFICATIONS ARE REQUIRED.
$HASP272 ENTER RESPONSE

```

Reply TERM to the \$HASP289/\$HASP272 message pair. You will then have to restart JES2 specifying the COLD (or FORMAT) option.

2. All options may be entered in uppercase or lowercase and must be separated by commas.
3. If two options are entered that are considered opposite, for example (WARM,COLD), the last option specified is the one JES uses.
4. If FORMAT is specified, the system will perform a cold start even though WARM is also specified.

The operator then enters the options using the standard reply format.

JES2 must be started and completely initialized before initiators will accept work.

Table 7. JES2 Start Options

Option	Explanation
FORMAT	FORMAT specifies that JES2 is to format all existing spool volumes. If you add unformatted spool volumes, JES2 automatically formats them whether FORMAT is specified or not. When you specify FORMAT, JES2 will automatically be cold started.
<u>NOFMT</u>	<p>Note: The FORMAT option is denied if this is a multi-access spool configuration, and JES2 is processing in one or more of the other members.</p> <p>Default: NOFMT specifies that JES2 is not to format existing spool volumes unless JES2 determines that formatting is required.</p>
COLD	COLD specifies that JES2 is to be cold started. All jobs in the member are lost.
<u>WARM</u>	<p>Notes:</p> <ol style="list-style-type: none"> 1. The COLD option is denied if this is a multi-access spool configuration and JES2 is processing in one or more of the other members. 2. If the member to be warm started is in a multi-access spool configuration with any other active members, only this member is warm started. <p>Default: WARM specifies that JES2 is to be warm started. JES2 will continue processing jobs from where they were stopped. If the FORMAT option was also coded, then JES2 will ignore the WARM specification and will cold start.</p>
NOREQ	NOREQ specifies that the \$HASP400 (ENTER REQUESTS) message is to be suppressed and that JES2 is to automatically start processing when initialization is complete.
<u>REQ</u>	<p>Default: REQ specifies that the \$HASP400 (ENTER REQUESTS) message is to be written at the console. This message allows the operator to restore the MVS environment (VTAM, for example) to what it was before the preceding shutdown and start JES2 processing with the \$\$ command.</p>

This can be overridden with OPTSDEF.

Table 7. JES2 Start Options (continued)

Option	Explanation
NOLIST	NOLIST specifies that JES2 is not to print the contents of the initialization data set or any error flags that occur during initialization. If you specify NOLIST, JES2 ignores any LIST control statements in the initialization data set. Figure 2 on page 20 presents an example of an initialization data set listing produced by using the list option.
<u>LIST</u>	<p>Default: LIST specifies that JES2 is to print all the statements in the initialization data set and any error flags that occur during initialization. (JES2 prints these statements if a printer is defined for that purpose when JES2 is started.) LIST will not print any statements that follow a NOLIST control statement in the initialization data set.</p> <p>This can be overridden with OPTSDEF.</p>
NOLOG	NOLOG specifies that JES2 is not to copy initialization statements or initialization errors to the HARDCPY console. If you specify NOLOG, JES2 ignores LOG control statements in the initialization data set.
<u>LOG</u>	<p>Default: LOG specifies that JES2 is to honor any LOG statements in the initialization data set.</p> <p>This can be overridden with OPTSDEF.</p>
SPOOL=VALIDATE	VALIDATE specifies that the track group map is validated on a JES2 all-member warm start.
SPOOL= <u>NOVALIDATE</u>	<p>This option when used in conjunction with job queue validation is useful for several special situations that require immediate track group map validation. Refer to “Rebuilding JES2 Job Queues” on page 45 for a further discussion of using SPOOL=VALIDATE.</p> <p>Default: SPOOL=NOVALIDATE specifies that the track group map is not validated when JES2 restarts (single-member and all-member warm start and hot start).</p>
CKPT1	CKPT1 specifies that JES2 reads the CKPT1 data set as the source of the checkpoint data for building the JES2 work queues.
CKPT2	CKPT2 specifies that JES2 reads the CKPT2 data set as the source of checkpoint data for building the JES2 work queues.
	<p>Note: This option is valid only on an all-member warm start.</p> <p>Default: If you do not specify this option, JES2 determines which checkpoint data set to initially read based on information in the checkpoint data set.</p> <p>This can be overridden with OPTSDEF or CKPTDEF.</p>

Table 7. JES2 Start Options (continued)

Option	Explanation
RECONFIG	<p>RECONFIG specifies that JES2 will use the checkpoint data set definitions as specified on the CKPTDEF statement in the initialization data set. JES2 overrides any modifications to the checkpoint data set definitions previously made either by the \$T CKPTDEF command or through the use of the checkpoint reconfiguration dialog. Specifying RECONFIG will also cause JES2 to enter the reconfiguration dialog during initialization; and issue message \$HASP289 CKPT1 AND/OR CKPT2 SPECIFICATIONS ARE REQUIRED. The CKPTDEF statement definition cannot contain the most current checkpoint definition if you have previously reconfigured your checkpoint configuration through the checkpoint reconfiguration dialog because changes made through the dialog are not saved in SYS1.VnRnMn.SHASPARM.</p> <p>Notes:</p> <ol style="list-style-type: none"> 1. This option is valid only on an all-member warm start. 2. Specifying PARM=RECONFIG has the same affect as specifying RECONFIG=YES on the CKPTDEF initialization statement.
HASPPARM=ddname	HASPPARM=ddname specifies the name of the data definition (DD) statement that defines the data set containing the initialization statements that JES2 is to use for this initialization.
HASPPARM= <u>HASPPARM</u>	<p>Default: HASPPARM=<u>HASPPARM</u> specifies that JES2 is to be initialized using the initialization statements in the data set defined by the HASPPARM DD statement in the JES2 procedure.</p>
CONSOLE	Causes JES2 to simulate receiving a CONSOLE initialization control statement after all initialization statements are processed. That is, if CONSOLE is specified, JES2 will divert to the operator console for further parameter input after all PARMLIB parameter input is exhausted. (Refer to the CONSOLE initialization control statement, above, for further information.)
NONE U N	<p>NONE, U, or N character specifies that JES2 is to use all the default start options. There is no difference between these three options. These options are equivalent. When NONE, U, Or N is specifie, JES2 uses the default start options which are:</p> <ul style="list-style-type: none"> • NOFMT • WARM • REQ • LIST • LOG
\$P JES2	If specified, instructs JES2 to terminate immediately.

Controlling Initialization Using JES2 Exits and the \$SCAN Facility

There are three exits taken by JES2 during initialization processing:

- Exit 0 for pre-initialization processing
- Exit 19 for initialization statement processing for each initialization statement
- Exit 24 for post-initialization processing

Each assists the JES2 initialization process by providing greater access to the initialization data set and increased checking and modifying capabilities.

If JES2 ends processing, Exit 26 can be taken for termination processing.

In addition, your installation can define new initialization statements, new parameters on existing statements, and JES2 options through the JES2 scanning facility. This facility scans input (JES2 initialization, control statements, and some operator commands), parses and validates the input, and sets or displays particular fields.

At each level of a scan, JES2 defines a table, and you can define an alternate table to override the JES2 table definition. These tables are used to determine the validity and content of each initialization statement scanned. The installation-defined table is used rather than the JES2 table. Thus, your installation can define your own statements, add parameters to JES2 statements, override the table definition for JES2 statements, or add messages. See *z/OS JES2 Installation Exits* for information concerning these exits and the scanning facility.

Controlling JES2 Load Modules

The following describes the structure of JES2 load modules and how they can be loaded onto your installation.

JES2 Load Modules

JES2 is comprised of three main load modules and a collection of subsystem support modules. In Table 8, the three mainload modules appear first, followed by the subsystem support modules.

Table 8. Subsystem Support Modules

Module	Purpose	Storage Location
HASJES20	The main task module.	JES2 private
HASPINIT	The initialization modules.	JES2 private
HASPFSSM	The functional subsystem service module.	FSS private
HASCARMS	Automatic restart management SSI support.	common
HASCARSO	Support for automatic restart management services.	common
HASCDAU	Supports the allocation of multiple spin \$IOTs to support multiple output characteristics.	common
HASCDLAL	Supports the allocation and deallocation of subsystem data sets.	common
HASCDLAL	Supports opening and closing subsystem data sets.	common
HASCDLAL	Supports any data spaces JES2 creates.	common

Table 8. Subsystem Support Modules (continued)

Module	Purpose	Storage Location
HASCENF	Event Notification Facility (ENF) LISTEN Exit	common
HASCGGKY	Supports generic grouping keys.	common
HASCGGST	Supports generic grouping strings.	common
HASCHAM	Contains the JES2 access method support.	common
HASCJBST	Supports job selection and job end processing.	common
HASCJBTR	Supports end-of-memory and end-of-task processing.	common
HASCLINK	Supports linkage between JES2 modules.	common
HASCOFST	Ensures the addressability of installation- or JES2-modified code.	common
HASCPOOL	Supports the JES2 cell pool services.	common
HASCRQUE	Request queue services.	common
HASCSAPI	Supports SYSOUT API (SAPI) requests	common
HASCSIJL	Supports checkpoint versioning.	common
HASCSIRQ	Supports miscellaneous subsystem interface (SSI) functions such as write-to-operator, commands, and process SYSOUT.	common
HASCSJFA	Updates the \$SJB with the output limits and the account number from the SWB.	common
HASCSJFS	Supplies SJF-related services.	common
HASCSRAX	JES2 AUX address space services.	common
HASCSRDS	Provides subsystem data set services.	common
HASCSRIC	Provides SSI control services.	common
HASCSRJB	Provides job-related services.	common
HASCTP	Provides APPC/MVS transaction program support.	common
HASCUBSR	Supports unwritten buffer processing.	common
HASCXJCT	Support for extensions to JCT.	common

HASJES20 resides in the JES2 address space, HASPINIT resides in the JES2address space during initialization processing, and HASPFSSM resides in the functional subsystem address space.

The JES2 subsystem support modules reside in either the common service area (CSA, if the modules are found in the STEPLIB or LINKLIST data set) or the pageable link pack area (LPA, if the modules are not found in the STEPLIB or LINKLIST data set).

Loading JES2 Subsystem Support Modules

You can control the area of storage into which JES2 loads these modules by placing copies of them in either the LNKLIST or STEPLIB data set before you start JES2. Modules loaded into LPA are read-only; they cannot be replaced. The copy JES2 uses depends on where JES2 finds these modules. This gives you the flexibility to use copies that reside in CSA instead of PLPA. Using copies that reside

in CSA eases migration and testing when your installation moves to a new level of JES2. If loaded into CSA, you do not need to IPL your member to obtain the new load modules following a JES2 restart.

Note: A hot start does not change the copies of subsystem support modules you are using.

See the STORAGE=CSA column of Table 9 on page 34 for details about which copy JES2 will use.

JES2 Subsystem Module Placement and Storage Considerations

All JES2 subsystem support modules normally reside above 16 megabytes in storage. The only exception is HASCHAM, the load module containing the JES2 access method. HASCHAM must support direct calls from applications running AMODE 24. All JES2 subsystem support modules run in 31-bit mode addressing at all times, except for a small part of HASCHAM. MVS facilities and applications that invoke JES2 services through the subsystem interface (SSI) can run in either 24-bit or 31-bit addressing mode. The SSI bridges to the 31-bit JES2 subsystem modules.

Controlling the Loading of Installation-Defined Load Modules

Use the LOADmod(jxxxxxxx) initialization statement to direct the loading of all installation-defined load modules (such as installation-defined exits). Exit routines should be loaded in this manner, rather than linking to JES2 load modules.

JES2 only searches for installation-defined exit routines in:

- User modules defined by the LOADmod(jxxxxxxx) statement
- HASPXIT0
- Modules with reserved names in the form HASPXJxx.

JES2 does not search for such routines in IBM-defined modules.

The STORAGE= parameter specifies the area of storage in which the load module is to be loaded. Table 9 presents a summary of the manner in which JES2 directs the load of a load module based on initial placement of that load module and the LOADmod(jxxxxxxx) STORAGE= specification.

Table 9. Placement of Load Modules Based on LOADmod(jxxxxxxx) STORAGE= Specification

Module is Located In:	LOADmod(x)		
	STORAGE=PVT	STORAGE=CSA	STORAGE=LPA
STEPLIB Only	PVT	CSA	\$HASP003 RC=31
LPA Only	LPA	LPA	LPA
LNKLST Only	PVT	CSA	\$HASP003 RC=31
STEPLIB and LPA	PVT (STEPLIB)	CSA (STEPLIB)	LPA version
STEPLIB and LNKLST	PVT (STEPLIB)	CSA (STEPLIB)	\$HASP003 RC=31
LPA and LNKLST	LPA	LPA	LPA
STEPLIB, LPA and LNKLST	PVT (STEPLIB)	CSA (STEPLIB)	LPA version

Note the following restrictions:

- **You cannot use the `LOADmod(jxxxxxxx)` statement to direct the load of any IBM-supplied JES2 modules.** If you specify any IBM-supplied JES2 modules on this statement, JES2 issues the following message:

```
$HASP003 RC=52, NO SELECTABLE ENTRIES FOUND MATCHING SPECIFICATIONS
```

The placement of these modules depends on which data set contains the modules. (See the `STORAGE=CSA` column in Table 9 on page 34 for the placement of the modules.)

- `STORAGE=LPA` is not valid if the load module is initially placed in STEPLIB only, LINKLIST only, or both STEPLIB and LINKLIST. JES2 issues message `$HASP003 RC=31, MODULE COULD NOT BE LOADED`.
- All other `STORAGE=` requests are valid, but you cannot receive the expected result (refer to Table 9 on page 34).
- You cannot load a module into the link pack area (LPA) following MVS initialization; you can only direct JES2 to use the LPA version.

Starting and Stopping JES2

MVS and JES2 initialization are two distinct processes. This means you specify the processes associated with initialization of MVS (reloading the LPA, clearing the VIO data sets) and of JES2 (initializing the job queues) separately. You can start both MVS and JES2 through either a cold start or some type of warm start. For more information on start types, see “Restarting JES2” on page 40. Although for any given IPL, it is possible to cold start one (MVS or JES2) and warm start the other, the usual procedure is a warm start for both.

JES2 performs an initialization the first time it is started (as part of the IPL procedure) and every time it is restarted. In a multi-access spool (MAS) configuration, you must start JES2 in each member in the configuration. The following provides information on starting and stopping JES2:

- “JES2 Program Properties”.

This topic describes the JES2 entry for the program properties table (PPT). The PPT allows an installation to specify a list of programs that require special attributes to run as efficiently and securely as possible.

- “Starting JES2 for the First Time (A Cold Start)” on page 36.

This topic describes the procedure for starting a JES2 member on a cold start (for the first time). It provides a record of JES2 message displays and the accompanying operator responses.

- “Performing an Orderly Shutdown of a JES2 Member” on page 38.

This topic describes how you can bring down a JES2 member, providing a record of JES2 message displays and the accompanying operator responses.

- “SMF Record Summary: Starting and Stopping JES2” on page 39.

This topic presents the SMF records generated whenever a JES2 member is started or stopped.

- “Using Event Notification Signalling with JES2” on page 40.

This topic describes how authorized programs can determine when JES2 starts or stops.

JES2 Program Properties

The JES2 entry of the program properties table (PPT) should indicate that JES2 is nonswappable because JES2 performs long-term page fixes. The program

properties table should also indicate that JES2 is a started task and is exempt from data set name enqueue and cancellation. Further, to ensure appropriate security checks for data sets opened by JES2 on behalf of user-submitted jobs, the PPT entry for JES2 **must** include password protection (PASS). The entry for JES2 in the IBM-supplied program properties table looks like this:

```
PPT PGMNAME(HASJES20) NOCANCEL NOSWAP NODSI PASS SYST KEY(1) LPREF
```

For information about defining the JES2 entry in the program properties table, see *z/OS MVS Initialization and Tuning Reference*.

Starting JES2 for the First Time (A Cold Start)

To start JES2 for the first time (a cold start) choose one of the following three methods:

1. Define your primary subsystem with the PRIMARY keyword in member IEFSSNxx on SYS1.PARMLIB.

The IEFSSN00 member defines JES2 as the primary subsystem and does not specify the NOSTART option. This causes JES2 to start automatically.

Because the IEFSSNxx member does not allow installations to pass parameters, you cannot use symbolic JCL if the START command is in the IEFSSNxx member of SYS1.PARMLIB. (Refer to *z/OS MVS Initialization and Tuning Reference* for more information about using this parmlib member.)

2. Specify the MVS START command in the COMMNDxx member of SYS1.PARMLIB.

3. Enter the **S JES2** command through an operator command:

In this example, the procedure that invokes the JES2 member is JES2.

```
S JES2,PARM=(COLD),M=initialization deck,N=parmlib member
```

Regardless of the method you use, specifying the JES2 start option LOG=NO decreases JES2 initialization time. The default for this JES2 start option, LOG=YES, specifies that JES2 must write all initialization statements and initialization errors to the HARDCPY console and the SYSLOG. You should only use the LOG=YES start option when testing a new initialization stream.

JES2 Console Messages During Initialization

As soon as JES2 is started, the SPECIFY OPTIONS message is issued to the operator. The operator then specifies the COLD parameter (or FORMAT) option.

A cold start results in the initialization of all JES2 job and output queues. During the spool processing for cold start, JES2 examines all spool volumes that are online to determine if each is formatted; any unformatted spool volume is formatted at this time.

If COLD (or FORMAT) is not specified, JES2 will issue the following series of messages:

```
$HASP479 UNABLE TO OBTAIN CKPT DATA SET LOCK
$HASP454 SHOULD JES2 BYPASS THE MULTI-MEMBER
INTEGRITY LOCK?
```

Reply 'Y' to this message, and then JES2 issues the following messages:


```

$HASP478 CONFIRM INITIAL CHECKPOINT READ FROM CKPTn
$HASP434 INVALID CHECKPOINT RECORD ON CKPTn DATASET
$HASP285 JES2 CHECKPOINT RECONFIGURATION IN PROGRESS
$HASP289 CKPT1 AND/OR CKPT2 SPECIFICATIONS ARE REQUIRED
$HASP272 ENTER RESPONSE

```

Reply 'TERM' to the \$HASP289/272 message pair. You will then have to restart JES2. Be certain to specify COLD (or FORMAT) when you again receive the \$HASP426 SPECIFY OPTIONS message.

If any of your checkpoint data sets reside on coupling facility structures rather than on DASD, JES2 issues the following message to verify the XCF connection, the JES2 XCF group name for your multi-access spool (MAS), and the name of the JES2 member that belongs to the JES2 XCF group:

```

IXZ0001I CONNECTION TO JESXCF COMPONENT ESTABLISHED,
          GROUP WSC      MEMBER WSC$SY01

```

For more information about how JES2 XCF groups are defined, see “Defining JES2 to the Cross-System Coupling Facility (XCF)” on page 9.

Regardless of where your checkpoint data sets reside, JES2 provides an informational message to display the size of the checkpoint that was determined from your initialization data set values. After receiving the checkpoint data set information, you must confirm that initialization should continue by responding 'Y' to the \$HASP441 message. For example:

```

$HASP537 THE CURRENT CHECKPOINT USES 43 4K RECORDS
$HASP436 CONFIRM COLD START ON
  CKPT1 - STRNAME=J2WRKCKPT1
  CKPT2 - STRNAME=J2WRKCKPT2
  SPOOL - PREFIX=J2WRK DSN=SYS2.HASPACE
03 $HASP441 REPLY 'Y' TO CONTINUE INITIALIZATION OR 'N'
      TO TERMINATE IN RESPONSE
$HASP478 INITIAL CHECKPOINT READ IS FROM CKPTn
      (STRNAME J2WRKCKPT1).

```

After you verify that JES2 should continue initialization, the member issues the following messages to start and format the JES2 address space:

```

$HASP493 JES2 COLD START IS IN PROGRESS
$HASP266 JES2 CKPT2 DATA SET IS BEING FORMATTED
$HASP267 JES2 CKPT2 DATA SET HAS BEEN SUCCESSFULLY FORMATTED
$HASP266 JES2 CKPT1 DATA SET IS BEING FORMATTED
$HASP267 JES2 CKPT1 DATA SET HAS BEEN SUCCESSFULLY FORMATTED
$HASP492 JES2 COLD START HAS COMPLETED

```

Once initialization is complete, JES2 deletes the \$HASP493 message and issues the \$HASP492 COLD START HAS COMPLETED message.

When JES2 completes initialization, it either

- Begins to process jobs automatically after the \$HASP492 message
- or
- Waits for the operator to enter the \$S command in response to the \$HASP400 ENTER REQUESTS message.

JES2 issues the \$HASP400 ENTER REQUESTS message if the PARM= keyword has been omitted from the S JES2 command and EXEC statement of the JES2 procedure.

A problem can occur if a JES2 spool volume (specified by the VOLUME= parameter on the SPOOLDEF initialization statement) is not mounted and ready when the primary JES2 member is started. At least one spool volume must be mounted because JES2 must have spool space available in order to process an MVS MOUNT command. In this situation, the operator must ready a spool volume and IPL again.

To be certain you have at least one spool volume available at all times, include an entry in the VATLSTxx parameter library member specifying at least one spool volume without suppressing the mount option. VATLST processing will then request that a volume be mounted during the IPL process. An example would be:

```
SP00L1,0,2,3380
```

See *z/OS MVS Initialization and Tuning Reference* for more information about VATLSTxx member.

Performing an Orderly Shutdown of a JES2 Member

You can stop and restart JES2 in a system at any time by using operator commands. This capability allows you to:

- Quiesce job processing in preparation for an orderly system shutdown
- Restart JES2 to perform an initialization with different initialization parameter specifications.

In each case, first enter the \$P command to drain the JES2 queues. (Note that all printers supported by a functional subsystem need to be drained prior to entering the \$P JES2 command). When all TSO/E users log off and all JES2 started tasks, logical initiators, printers, and punches complete their current activities and become inactive, JES2 notifies you with the following message:

```
$HASP099 ALL AVAILABLE FUNCTIONS COMPLETE
```

You can then stop all started tasks and enter the \$P JES2 command, which stops JES2 and removes it from the MVS system.

If an installation is running partially disabled because a PCE (processor controller element) has failed, you must enter the \$P JES2,ABEND command because the member cannot end without an abnormal termination. JES2 informs an installation if it is running with a disabled processor through the \$HASP068 message, which identifies the processor that has failed. For more information about JES2 PCE recovery options see “Running With Disabled JES2 Processors”.

When you are halting the system at the end of the day or the end of the work shift, you can enter the MVS HALT EOD command to bring down the MVS system. If you halt the MVS system, refer to “Restarting JES2” on page 40 for instructions on how to restart the JES2 member.

Running With Disabled JES2 Processors

Processor control elements (PCEs) represent dispatchable work in JES2; there are PCEs for devices such as printers, lines, transmitters, and readers, as well as for functions such as conversion, execution, output, and purge.

JES2 recovery processing deactivates non-essential PCEs in the event of a failure. This procedure allows JES2 to continue processing work with all but the failing device or function. The installation can then decide when to restart JES2 and control the number of unexpected JES2 outages. Non-essential PCEs are not critical to the operation of the JES2 subsystem. However, system programmers must determine the relative importance of a particular PCE to their installation. Refer to the complete list of JES2 PCEs in *z/OS JES2 Diagnosis*.

It is not recommended that installations continue processing work for a long time without a PCE because JES2 may lose some function. For example, if a spool processor fails, an installation could not issue commands to start, halt, or drain a spool volume. If a printer PCE fails, an installation would not be able to print output owned by that processor on another printer.

If a printer PCE fails while a SYSOUT transmitter is in the process of transmitting a large job across the network, an installation can run without the printer PCE until the SYSOUT transmitter finishes transmitting the data. Once the SYSOUT transmitter has finished, an operator should bring JES2 down by entering a \$P JES2,ABEND command, then hot start the subsystem to reacquire the failed PCE.

When a PCE fails:

- JES2 attempts normal recovery through \$ESTAE processing. If \$ESTAE recovery processing is successful, JES2 processing continues.
- If the PCE is not recoverable and is essential to the proper operation of JES2, then JES2 will end.
- If the \$ESTAE routine cannot recover the PCE, and the device or function that the PCE represents is not essential to JES2, the PCE will never be given control again; JES2 will not attempt to recover the resources associated with the lost PCE and issues the \$HASP070 message.

Note: The \$HASP070 message occurs only if the number of ABENDs has exceeded the threshold set by the RECVOPTS(MAIN) initialization statement.

You can then decide if and when the lost PCE warrants a restart of JES2. See *z/OS JES2 Messages* for information about \$HASP095 and \$HASP068.

SMF Record Summary: Starting and Stopping JES2

The following lists the SMF records written when a JES2 subsystem is started and stopped. For a complete list of the record contents, see *z/OS MVS System Management Facilities (SMF)*.

Table 10. SMF Records Used When JES2 Starts or Stops a Member

Record Number	Action that Causes the Record to be Written
43	<ul style="list-style-type: none"> • An operator enters a \$S JES2 command. • An operator enters a \$E MEM command.
45	<ul style="list-style-type: none"> • An operator brings down the JES2 address space (\$P JES2 command). • JES2 ends abnormally and retains control long enough to write the record.

Using Event Notification Signalling with JES2

Authorized programs can determine when JES2 is started by listening for ENF (event notification facility) signal 40. Any application program that relies on the JES2 member can tell when a primary or secondary JES2 begins or ends normally.

Authorized programs can determine when JES2 is ending normally by listening for ENF signal 40. ENF signal listeners are not notified if JES2 ends abnormally. For more information about how to specify the ENF signal, see *z/OS MVS Programming: Authorized Assembler Services Guide*.

Restarting JES2

You can restart JES2 by either selecting a cold start or a type of warm start. This selection is made when the operator responds to the SPECIFY OPTION request with either COLD or WARM. The restart type you select depends on the current environment within a single processor or multi-access spool (MAS) configuration. Refer to “Modifying JES2 Initialization Statement Specifications” on page 48 for notes on when a particular type of restart is required.

The following describes:

- “Cold Start”
This topic describes how you can start JES2 through a cold start.
- Warm Starts
This topic describes how a JES2 member can be warm started.
- “Warm Start Considerations” on page 43
This topic describes how JES2 processes the job queues during warm starts and what you can do to secure jobs across a restart.
- “Hot Start Considerations” on page 46
This topic describes how JES2 processes initialization statements and functional subsystem devices across a restart.
- “Restarting JES2 after an Orderly Shutdown” on page 47
This topic describes how you can restart the JES2 address space if the MVS system is still running.
- “Specifying Job Journaling to Ease Restart Processing” on page 48
This topic cites the benefits of maintaining a job journal data set on a JES2 SPOOL volume.

Cold Start

On a restart of a JES2 member, you should implement a cold start with some caution, because all job data previously on the spool volumes is lost. No other member in a multi-access spool configuration can be active during a cold start, or JES2 will end with an error message.

If you request a cold start of JES2 or have specified the FORMAT start option, an IPL must precede the execution of the MVS START(S JES2) command. However, an IPL is not required if JES2 was stopped by a \$P JES2 operator command.

Warm Starts

There are five ways in which a warm start can be performed in a multi-access spool configuration. The following explains how you can use these options and the processing that JES2 performs.

All-Member Warm Start

An all-member warm start is performed if a warm start is specified by the operator and JES2 determines that no other members of the configuration are active or there is only one member in the configuration. All in-process work in the MAS will be recovered. After an all-member warm start, other members entering the configuration for the first time will perform a quick start.

This is the only time that certain activities are performed within the MAS, because no other processors are currently using the checkpoint data set. These activities include:

- Rebuilding the track allocation status (track group map) if you specify SPOOL=VALIDATE as a start option.
- Validating (and rebuilding when necessary) the job and output queues and the job queue index. Damaged or corrupted job output elements (JOEs) and job queue elements (JQEs) are placed on the rebuild queue.
- Deleting spool volumes not previously removed through the \$P or \$Z commands that are no longer available to the member. Refer to “Starting the Multi-Access Spool Configuration” on page 58 for starting JES2 in a multi-access spool configuration.

Note: You can add members of a multi-access spool configuration at any JES2 warm start.

Single-Member Warm Start

A single-member warm start is performed when WARM is specified and other members of the configuration are active. The warm-starting member joins the active configuration and recovers only work in process on that member when it failed or was stopped.

If JES2 experiences an abnormal termination (ABEND), and you wish to request a JES2 warm start:

1. IPL the system.
2. Issue the MVS START JES2 COMMAND.
3. When a request for options (SPECIFY OPTIONS) is received at the console, respond with the keyword WARM.
4. In a multi-access spool configuration, all spool volumes that are online to the multi-access spool configuration must also be online to the member being started.

When warm starting, JES2:

- Only requeues jobs that were previously active on this processor.
- Validates and rebuilds when necessary the job and output queues and the job queue index. Damaged or corrupted job output elements (JOEs) and job queue elements (JQEs) are placed on the rebuild queue.

Quick Start

You can perform a quick start when you respond with the keyword WARM to the request for options (\$HASP426 SPECIFY OPTIONS) at the console and JES2 determines that the job queue and job output table do not need to be updated. In this case, the member being started is **not** the first member being started in the MAS. This can occur in these circumstances:

- After \$P JES2 has been issued to quiesce the member. Because all work is quiesced, there is no need to update the job queue or job output table before restarting.

- After an all-member warm start has been performed and no work is waiting to be processed; therefore, the job and output queues are empty.
- A \$E MEM command was entered at a processor within the multi-access spool configuration other than the member being started. This gives the issuing member the ability to:
 - Process any jobs that had a specific affinity for the member being reset.
 - Process any output for the reset member.
 - Restart any jobs that were interrupted on the reset member.
 - Dynamically add a new member to a multi-access spool configuration. A new member is defined as a member that has a NAME (on the MEMBER statement) that has not been previously defined to the MAS.

Thus, there is no need to update the job queues or job output table on the reset member.

On a quick start, as on all other start types, JES2 validates (and rebuilds when necessary) the job and output queues and the job queue index. Damaged or corrupted job output elements (JOEs) and job queue elements (JQEs) are placed on the rebuild queue.

Hot Start

A hot start is performed when JES2 abnormally terminates, WARM is specified, and JES2 determines that an IPL has not occurred prior to restart.

You can use a hot start when JES2 has stopped, but other members have continued to function and have not experienced problems. When you hot start JES2, all address spaces continue to execute as if JES2 had never terminated. Functional subsystems will continue to process spooled output as long as possible before the hot start, and JES2 will reconnect to the functional subsystem (FSS) during the hot start. Hot starts do not affect other members in a multi-access spool configuration.

JES2 validates (and rebuilds when necessary) the job and output queues and the job queue index. Damaged or corrupted job output elements (JOEs) and job queue elements (JQEs) are placed on the rebuild queue.

Also, many initialization statements and parameter specifications are ignored on a hot start of JES2. (*z/OS JES2 Initialization and Tuning Reference* notes these parameters.)

\$E MEM Command Start

In addition to the above methods of restarting JES2, a restart of work on the failed member can be performed on any other active member in the configuration by the AUTOEMEM facility or by entering the \$E MEM command. In-process work on the specified member is recovered and made available for selection by other members of the configuration, subject to system affinity for execution restart.

Table 11 on page 43 shows which type of warm start is appropriate, depending on

- How the JES2 member was shut down
- Whether other JES2 members are active.

Table 11. Warm Start Types

Warm Start Type	Other Members Active	Circumstances for Doing a JES2 Warm Start
All Members*	No	IPL or \$P JES2
Single member	Yes	Abend followed by MVS IPL
Quick	Yes	For any of the following: <ul style="list-style-type: none"> • \$P JES2 (with or without IPL) • After first member in an all-member warm start • After a \$E MEMBER command or the AUTOEMEM option performed from another member of the MAS • Dynamically add a new member • When adding an already defined member to a MAS
Hot	N/A	Abend without MVS IPL
Note: If there are no other members active in the MAS, JES2 performs an all member warm start.		

Warm Start Considerations

If HARDCPY=SYSLOG (in the IEASYSxx parameter list) is specified and MVS system WTO buffers in use exceeds the limit specified in the CONSOLxx MVS statement, JES2 will be placed in a wait until the buffers in use again falls below that limit.

During a warm-start initialization, JES2 reads through its job queues and handles each job according to its status:

1. Jobs in input readers are lost and must be reentered.
2. Jobs in output (print/punch) are requeued and later restarted.
The checkpoint for jobs on the 3800 printer points to the end of the page being stacked at the time of the checkpoint. Jobs that were sent to the 3800 printer but that did not reach the stacker are reprinted from the checkpoint. If no checkpoint exists, then it is reprinted from the beginning.
3. Jobs in execution are either requeued for execution processing or are queued for output processing.
4. All other jobs remain on their current queues.

If a job in execution was journaled, it is updated to indicate warm start, and the job is queued for re-execution. If a job in execution has no journal, it is tested to determine whether restart was indicated for the job. If *restart* was indicated, the job is updated to remove any warm-start indications, and the job is queued for re-execution. If restart was not indicated, the job is queued for output processing.

Following JES2 warm-start processing, jobs queued for re-execution are again selected by initiators.

- A nonjournaled job that was requeued because RESTART was indicated is handled as a new job.
- A journaled job that indicates warm-start processing receives special attention from an initiator.

The initiator/terminator purges existing job tables and messages for the job and then checks whether the job is authorized for warm-start processing:

- The job must have a valid restart definition (RD=) code in the RD parameter on its JOB statement.
- The operator must authorize the job to be restarted. (Each eligible job is presented to the operator asking whether the job is to be restarted.)

If either of these two authorizations is not made, the job is tested to determine whether RESTART was indicated. If it was, the job's JES2 job control table control block is updated to remove any warm-start indications, and the job is queued for re-execution. If restart was not indicated, the job is queued for output processing.

Jobs can be presented to the JES2 member for warm start at any time and in any order. This allows important jobs and member functions to be executed ahead of less important jobs scheduled for execution or termination. New jobs can be presented to the JES2 member and processed according to their priority, ahead of lower-priority warm-start jobs.

During warm-start initialization, JES2 lists the activity in process for each job at the time JES2 was stopped. Then, when the ENTER REQUESTS message is issued (unless the NOREQ start option was specified), the operator can enter requests to modify or delete each activity. This message also allows the operator to examine the status of output devices (such as UCS and FCB settings) in order to:

1. Determine what action should be taken prior to restarting the output process
2. Change the status of logical initiators and devices
3. Modify the status of jobs on the JES2 queues.

The status and activity of each device will revert to the specifications of the initialization parameters. If you specify NOREQ, JES2 begins processing each job according to the specifications of the initialization parameters as soon as resources to process each job become available.

Warm Starting with Multiple JES2 Levels in a MAS: JES2 supports up to 4 consecutive releases of JES2 running in the same MAS. JES2 enforces this rule and ships service to down level releases to allow them to exist with the newer releases. Failure to apply this maintenance or trying to go outside the supported release will result in a \$HASP710 message being issued to indicate the problem. \$HASP710 indicates active members in the MAS are incompatible with the initializing member. See the JES2 Messages book for more information.

JES2 also supports a more liberal migration policy. This migration policy covers going from one release of JES2 to a new release with a warm start. IBM guarantees that this migration policy will span a *minimum* of 5 releases of the operating systems. That is, the data generated by the JES2 provided with release x of the operating system is compatible with the data generated by the release of JES2 provided with release x-5 and release x+5 of the operating system. This may include a release that cannot coexist in a MAS. The requirements for migration are documented in the JES2 Migration manual for each release. Failure to abide by the migration requirements can result in a \$HASP446 message being issued. For more information on \$HASP446 see JES2 Messages.

Verifying Checkpoint Time Stamps: During warm start processing, JES2 performs some checks on the last written time stamps of the checkpoint data sets it is going to use. These tests try to detect cases where JES2 is reading from the wrong checkpoint data set. Ultimately it is the installations responsibility to ensure that the correct data sets are used to start JES2. However, some common problems are detected by JES2. Normally, the \$HASP478 message is not highlighted and is issued for informational purposes only. However, if JES2 detects a potential

problem with the last written times of the checkpoint data set(s), then the message is highlighted and followed by the \$HASP441 WTOR. When this happens, the installation should verify that the time stamps associated with the data set compared with the time the MAS was last active and would have last written the checkpoint. If not, then reply 'N' to the \$HASP441 message to terminate in response to \$HASP478.

Rebuilding JES2 Job Queues: Errors that are not detected and corrected by other portions of JES2 can damage the JES2 job or output queues. These errors can occur in both software and hardware. You can correct these errors through any type of warm start if all active members of the MAS are at JES2 SP5.2 or higher. Because the original in-storage order of jobs might change as a result of the job queue rebuild, JES2 performs the queue rebuild only with operator permission. To indicate a job queue error and request operator instruction, JES2 issues \$HASP483 JES2 JOB QUEUE ERROR -- REPLY 'Y' TO REBUILD OR 'N' to TERMINATE JES2.

When job queues are rebuilt, JES2 invokes the REQ initialization option, allowing jobs to be requeued or cancelled at your discretion.

The success of the queue rebuild procedure depends upon how badly the queues are damaged. If there is insufficient information to permit rebuilding the queues for a job, that job is purged and must be resubmitted for processing.

When you warm start JES2, JES2 verifies data that includes the following:

- For JQEs:
 - Job number is non-zero and not used by any other job
 - Valid offset to next JQE
- For all JOEs:
 - The JOE type compared to the queue type
- For work JOEs:
 - The class type
 - The offset of the job queue element
 - The offset of the characteristics JOE.

If JES2 detects that the JQE or JOE has been corrupted and JES2 cannot correct the problem, JES2 places that JQE or JOE on the **rebuild queue** until it can be moved to the free queue. (To be moved to the free queue, a JQE must not be locked, busy, or retain JOEs.) JES2 moves the JQE or JOE when the member is again restarted, at the next all-member warm start, or when that JQE or JOE is no longer busy (that is, when this phase of job processing ends).

If in response to a \$D JOBDEF or \$D OUTDEF command, JES2 indicates that there are jobs or JOEs, respectively, on the rebuild queues, use the \$D REBLD command to display all jobs and output elements on that rebuild queue. This might prove useful when trying to locate jobs that appear lost; a situation that might occur if in response to a \$D J, \$L J, or a \$D OJ command JES2 does not find all the jobs you expected.

Typically, the rebuild queue is empty, but if JES2 places a job or JOE on the rebuild queue, it provides diagnostic information through messages \$HASP440 and \$HASP517 when it completes rebuilding the JOE queue and JQE queue, respectively. These messages also include the number of elements placed on the rebuild queue.

Validation of JES2 Track Group Map: On an all-member warm start, you can use the SPOOL=VALIDATE start option to request that JES2 validate the track group map. This is typically not needed unless you receive indications from JES2 such as the following:

- Persistent JES2 disastrous errors (\$HASP095, error code \$DIS)
- LOGREC symptoms records (SYMRECs) that point to track group allocation or purge problems.

Not all SYMRECs warrant your use of SPOOL=VALIDATE. Some of the symptom records are considered informational only. Refer to *z/OS JES2 Diagnosis* for a list of the SYMRECs and an indication of their severity.

Immediate spool validation can then be useful as an immediate validation of the track group map in place of the ongoing track group validation cycle wherein all track groups are validated once every 7 days.

If JES2 rebuilds the job queues, JES2 forces track group validation on the next all-member warm start. If that rebuild occurs during an all-member warm start, the track group validation occurs during that warm start; it does not wait until the next all-member warm start.

Restarting JES2 with Missing Spool Volumes: During all-member warm-start processing, the operator is notified of any spool volumes not mounted, and is requested to provide information concerning their status. If a spool volume cannot be recovered, the operator's response (PURGE) will force the purging of jobs and SYSOUT data sets allocated to the volume. If the operator indicates that the volume is only temporarily unavailable (GO), no jobs allocated to that volume will be processed until the volume is made available through a \$\$ SPL command. If the required volumes have not been mounted at this point, the operator can end (QUIT) JES2 initialization.

Note: If JES2 is interrupted during spool validation (through either an abnormal end or a re-IPL), JES2 does not provide the GO option to the operator.

For information on the relationship between restarting and use of the checkpoint data set, refer "Checkpoint Reconfiguration, An Overview" on page 228.

Hot Start Considerations

Initialization Statements: A hot start will cause certain initialization statements and initialization statement parameters to be ignored. For the complete set of ignored parameters, consult the parameter description for each JES2 initialization statement in *z/OS JES2 Initialization and Tuning Reference*.

Exit Facility: If JES2 is hot starting, it is possible that some jobs have not finished execution; these jobs could still be calling installation exit routines from one of the JES2 subsystem support load modules. Therefore, the names, number, and order of the exit routines for each exit are required to remain unchanged, and all EXIT(nnn) initialization statements encountered during a hot start are ignored.

You can change the exit routine addresses through the LOADmod(jxxxxxxx) statement, with the restriction that routines previously loaded into the private area remain there and those in commonly addressable storage (PLPA or CSA) remain there.

The only exit facility initialization processing that takes place during a hot start is the resolution of exit routine addresses from installation load modules reloaded into the private area.

Functional Subsystem Reconnection: Functional subsystem reconnection during a hot start requires considerations similar to those of exits. Because some jobs might have not finished printing, these jobs might still require the support of previously-defined functional subsystems. Therefore, the names and number of any defined functional subsystems must not change across a hot start; if they are changed, those changes are ignored.

If a previously started functional subsystem printer successfully reconnects to JES2 during a hot start, the settings for the following PRT(nnnn) initialization statement parameters are retained across the hot start and the values specified during initialization are ignored:

- BURST=
- COPYMARK=
- FCBIC=
- FLASHIO=
- Forms=
- MARK=
- PRESELECT=
- SEPDS=
- SEP=
- SETUP=
- TRace=
- TRKCELL=
- UCSIT
- UNIT=

JES2 honors all other PRT(nnnn) initialization statement parameters during a hot start.

Restarting JES2 after an Orderly Shutdown

If you do not halt the MVS system after stopping JES2, JES2 can be restarted with the S JES2 command. As part of this command, you can specify your start options as parameters; for example:

```
S JES2,PARM='WARM,HASPPARM=PARMRJE,NOREQ'
```

When you specify the options on the START command in this manner, JES2 suppresses the \$HASP426 SPECIFY OPTIONS message, just as it does when you specify the options as parameters on the EXEC statement within the JES2 procedure.

You can also use the START command to specify a printer address for the HASPLIST DD statement in the JES2 procedure; for example:

```
S JES2,00E
```

If you specify both a printer address and initialization options, the printer address must be specified first:

```
S JES2,00E,PARM='WARM'
```

Restarting JES2 after a System Failure

JES2 is restarted automatically in an MVS system whenever that system IPL is repeated following a system failure. The WARM start option allows you to warm start JES2 and continue job processing from the point of the last checkpoint before the member failure.

Specifying Job Journaling to Ease Restart Processing

The job journal is a temporary sequential data set that resides on a JES2 spool volume. It preserves a set of selected job-related control blocks that are necessary for restart processing for the following situations: automatic step (using the RD= parameter on the JCL JOB statement), automatic checkpoint, continue, and JES2 member warm starts.

The job journal is necessary because the scheduler control blocks, maintained in the scheduler work area (SWA), are otherwise lost when a job abnormally ends. Reconstruction of the SWA is possible because the job journal preserves up-to-date copies of essential control blocks.

Unless you specify no job journal by defining JOURNAL=NO on the JOBCCLASS initialization statement, each job is provided with a job journal. If you are using checkpoint restart or need to restart a job step, you need a job journal or automatic restarting will not be possible (and jobs that are executing during member failure need to be resubmitted).

However, if you are using Automatic Restart Management to restart a job, you should use non-journaled classes.

Note that job journaling can cause some performance degradation. For further information regarding the JOURNAL parameter, refer to the JOBCCLASS initialization statements in *z/OS JES2 Initialization and Tuning Reference*.

Modifying JES2 Initialization Statement Specifications

If you are restarting JES2 for the purpose of changing initialization statements or parameter values, a cold start is only required for a limited number of JES2 parameters. A warm start can often be used for most parameters, or a specific \$T operator command might suffice. The level of minimal JES2 disruption and operator intervention is listed for each JES2 initialization parameter under the heading 'Modification:' within the full parameter descriptions in *z/OS JES2 Initialization and Tuning Reference*. Study these before restarting JES2 for the purpose of initialization parameter specification modification. You might be able to avoid a JES2 warm or cold start. The modification heading is listed for all parameters on all statements; it is specified as follows, with the minimal intervention level:

Table 12. Modification Heading

Minimal Modification	Meaning
COLD START	Only a cold start can be used to modify this parameter.
WARM START	A warm start is required to modify this parameter; a cold start can be used. (To understand the different types of warm starts, refer to "Restarting JES2" on page 40.)

Table 12. Modification Heading (continued)

Minimal Modification	Meaning
Operator Command	This parameter can be modified by a specific \$T operator command. Refer to <i>z/OS JES2 Commands</i> for a full description of the \$T command. This parameter might, or might not, also be modifiable by any type of WARM start, or a COLD start. (Some parameters can be modified only by \$T command or cold start; these are noted within the parameter descriptions in <i>z/OS JES2 Initialization and Tuning Reference</i> .)

Most JES2 initialization parameters can be displayed by the \$D operator command. Particularly for tuning purposes, the operator can ask JES2 for the current setting of many JES2 parameters. In this manner, both the operator and the system programmers can be aware of the JES2 environment.

Dynamic display and modification of the JES2 initialization parameters can be used to ease the tuning of your MVS system without unnecessarily disrupting system processing and decrease your installation's need for planned system outages.

How to Correct Initialization Errors

During JES2 initialization, two kinds of errors can occur. The first can occur when JES2 cannot open the data set containing the initialization statements. This happens, for instance, when a DD statement is named in the HASPPARM=ddname start option, but the named DD statement is not defined in the JES procedure. JES2 acknowledges the error with the following messages:

```
$HASP450 OPEN FAILED FOR JES2 PARAMETER LIBRARY
$HASP441 REPLY Y TO CONTINUE INITIALIZATION OR N TO TERMINATE
```

The second message allows the operator to restart initialization processing with a correctly defined data set.

The second error can occur when JES2 encounters an error in the statements in the initialization data set. Initially, JES2 goes into CONSOLE mode, and the operator is informed of the statement in error. Also, JES2 flags each statement in error and reads the next one in the data set. If the data set is printed out, each statement that was in error will have an error message (\$HASP467) printed beside it. (See "Specifying the Start Options" on page 27 for a description of the LIST option and Figure 1 on page 17 for an example of these diagnostic messages.) The text of the \$HASP267 diagnostic messages and an explanation of each is listed in *z/OS JES2 Messages*.

If any errors were encountered (when not in console mode) after all parameter statements have been read, JES2 issues the following messages:

```
$HASP451 ERROR ON JES2 PARAMETER LIBRARY
$HASP441 REPLY Y TO CONTINUE INITIALIZATION OR N TO TERMINATE
```

The operator's reply should be based on a careful examination of the initialization statement. If the reply is N, JES2 issues the following message:

```
$HASP428 CORRECT THE ABOVE PROBLEMS AND RESTART JES2
```

When you have included a JES2 initialization statement that contains a parameter specification that is in error, JES2 will ignore the entire statement and do one of the following:

- If the statement was previously specified, obtain whatever explicitly-defined parameter values were coded or defaulted and use these values during the initialization
- If the statement was not previously specified, provide default values for all the parameters on that statement that have JES2 defaults.

Poly-JES

The term “poly-JES” refers to the concurrent operation of multiple copies of JES2. MVS allows more than one JES2 subsystem to operate at a time, as long as one subsystem is designated as the primary subsystem and others are identified as secondary subsystems. Secondary JES2s can be useful in testing user modifications while the primary JES2 is being used for production.

You might also find a secondary JES2 system to be useful when you need to test a new initialization data set, that is as an “init-deck checker” prior to running that data set on your production system.

You should replace a few specifications in the initialization deck so that the secondary JES2 does not conflict with the production JES2.

- CKPTDEF - use different data set names or volumes
- SPOOLDEF - use different volumes
- CONDEF - use a different CONCHAR so that you can communicate with the secondary JES2

Certain operational considerations and restrictions apply to the secondary JES2:

- You can start primary and secondary subsystems in any order.
- Started tasks (STCs) can be directed to either a primary or secondary JES. However, once you identify a subsystem as a secondary, you cannot run started tasks (STCs) under that secondary unless you have initialized the primary at least once during this IPL. Attempting to run started tasks on a secondary without starting a primary at some time during this IPL can cause JES2 to become hung, forcing an installation to re-IPL.
- Time-sharing users (TSUs) can only interface with the primary JES.
- The MVS I/O attention table can only be associated with the primary JES. Therefore, secondary JESs cannot receive the “unsolicited interrupt” required to support pause-mode for print and punch devices and “hot readers” (that is, readers started by the physical start button without the \$\$ RDR(n) JES2 command).
- The MVS log console (SYSLOG) can only be associated with the primary JES.
- Secondary subsystems are started individually rather than automatically during IPL using the IEFSSNxx parmlib member.
- If the primary and secondary JESs are in the same MAS, a job restarted by automatic restart management will have affinity to both the primary and the secondary JESs. A job can run in the primary and rerun in the secondary, if there are initiators on both JESs capable of selecting the job. If you don’t want jobs to have affinity to both JESs, you should segregate the job classes between the primary and the secondary JESs.

When running more than one JES2 at a time, it is necessary to assign (by use of the CONCHAR= parameter on the CONDEF initialization statement) a unique operator command character to each JES2. If the secondary subsystem is not part of the same multi-access spool complex, each JES2 member requires both a unique spool data set (specified on the VOLUME= parameter of the SPOOLDEF initialization statement) and a unique checkpoint direct access device (specified on the CKPTn=(...,VOL=) parameter of the CKPTDEF initialization statement). Also, the keyword “JES2” must be used to stop whatever subsystem is running, regardless of the name on the START command; for example:

```
S  JES2      START JES2
$P JES2      STOP  JES2      (default CONCHAR)
START JSS4    START  JSS4
/P JES2      STOP  JSS4      (CONCHAR=/)
```

Many of the considerations for running a primary JES are also appropriate for running a secondary JES; note the following:

- The subsystem support module required by the secondary subsystem, must be placed in either the link pack area (LPA) or the common service area (CSA). See Table 9 on page 34, for more information.

Notes:

1. It is recommended that a STEPLIB data set be used for the secondary subsystem if the subsystem support module is different than the one in use by the primary system.
 2. When the same copies of the JES2 subsystem support modules are in use by both the primary and secondary subsystems, minimize your storage use by making sure that the JES2 subsystem support modules are loaded into LPA.
- If the secondary subsystem is placed in a library other than SYS1.VnRnMn.SHASLINK or a LNKLIST library, that data set name must be added as a member to the APF (authorized program facility) specification list in order to authorize it. (See *z/OS MVS Initialization and Tuning Guide* for a complete description of this procedure.)
 - If a name other than HASJES20 is used for the main module (this is not recommended) that name must be added to the program properties table such that the program runs in protect key 1 and is nonswappable.

Defining a Secondary JES2 Member to MVS

Define and add secondary subsystems to MVS by defining the subsystems in the SYS1.PARMLIB member IEFSSNxx. These members contain lists of subsystems to be defined to MVS during master scheduler initialization. The SSN option can be specified when the system parameters are initialized or in IEASYSxx. (IEFSSN00 is reserved for IBM use.) The syntax for the SSN option is as follows:

```
SSN=(aa,bb,...)
```

This is the recommended method for defining and modifying a secondary subsystem. Refer to *z/OS MVS Initialization and Tuning Guide* for further information.

Installing a JES2 Secondary Subsystem

The following steps show how an installation might install a secondary subsystem. The assemblies and link edits can be accomplished by using the System Modification Program/E (SMP/E) (refer to *z/OS SMP/E User's Guide* for a

description of this technique) or by using your own JCL. Examples of assembly and link edit procedures are provided in the HASIBLD member of the JES2 distribution library.

Note that JESA (the secondary member) must be added to a IEFSSNxx member of SYS1.PARMLIB.

1. Create a JESA PROC, which defines the secondary JES2's parmlib as 'JESPARM' (See sample below.)

//JESA	PROC	M=JESAPARM,U=3380,L=LINKLIB,N=SEC,
//		V=SYSRES
//IEFPROC	EXEC	PGM=HASJES20,TIME=1440
//STEPLIB	DD	UNIT=3380,VOL=SER=&V,DISP=SHR,
//		DSN=&N;.&L;
//PROC00	DD	DSN=SYS1.PROCLIB,DISP=SHR
//HASPPARM	DD	DSN=&SYS1;&PARMLIB;(&M),DISP=SHR,UNIT=&U *
//HASPLIST	DD	DDNAME=IEFRDER

Note: Libraries specified in the JES2 procedure must be referred to in one of the following ways:

- Cataloged in the master catalog
- Specify UNIT= and VOL= on the JCL DD statement
- Managed by SMS (UNIT= and VOL= on the JCL DD statement are ignored.)

2. Create load modules in a separate, APF-authorized library. This library should be cataloged in the master catalog. For more information on how to perform this task, see *z/OS MVS Initialization and Tuning Reference*.
3. If the checkpoint data set(s) resides on a direct access storage device (DASD), specify them through the DSN= and VOLSER= subparameters on the CKPTn= parameters of the CKPTDEF initialization statement. If the checkpoint data set(s) resides on a coupling facility structure, specify the structures through the STRNAME= subparameter on the CKPTn= parameters of the CKPTDEF initialization statement.

When the checkpoint data sets reside on DASD, they are often named SYSn.JESCKPT1 and SYSn.JESCKPT2, where 'n' represents any number from 0-9.

A checkpoint data set on a coupling facility structure must refer to a predefined structure. For an example of the definitions necessary for JES2 checkpoints on coupling facilities, see "Placement of the Checkpoint Data Set" on page 196. For checkpoints residing on a coupling facility structure, IBM recommends using a name without a period, such as SYSn_J2WRKCKPT1 and SYSn_J2WRKCKPT2, to differentiate from DASD.

4. Allocate a spool data set, using the name SYSn.HASPACE, and place it on a particular volume (many use SECJ2, but the volume name is optional).
5. Specify options to the primary JES2 member when it enters initialization.
6. If you intend to use a functional subsystem (FSS), add or modify any cataloged procedures for functional subsystems that run under the secondary subsystem. Ensure that the correct version of the HASPFSSM load module is used.

The internal START command that JES2 uses to start a functional subsystem (FSS) cannot contain variable operands to specify STEPLIB information. Therefore, if multiple versions of the JES2 are maintained in separate libraries, you might need to maintain multiple versions of the FSS cataloged procedure(s) and vary the PROC= keyword of the FSS initialization statement.

7. Issue an 'S JESA' MVS command once the primary member is active.

The secondary JES2 proclib member (referred to as 'JESA' on the MVS START command) points to the JES2 initialization data set that defines the primary checkpoint data set to a coupling facility structure and allocates the secondary checkpoint to a DASD volume. The following is an example of the initialization statements:

```
CKPTDEF    CKPT1=(STR=SYS1.WRKCKPT1,INUSE=YES)
           CKPT2=(DSN=SYS1.JESCKPT2,VOL=SECJ2,INUSE=YES)
SPOOLDEF   VOLUME=SECJ2
CONDEF     CONCHAR=/
.
.
.
```

To execute this procedure and obtain a listing of the initialization deck for secondary subsystem JESA on printer 00E, enter the following command:

```
S    JESA,UNIT=00E,
```

Enabling the AUTOEMEM Option on a Secondary Subsystem: If both the primary and the secondary JES2 subsystem use the AUTOEMEM option to make jobs from failed members eligible for restart on another member, (AUTOEMEM=ON on the MASDEF initialization statement), you must ensure that they have distinct member names. Because the node name is from the NAME= parameter on the NODE(nnnn) initialization statement, ensure that the primary and secondary JES2 member have different variables for at least one of the parameters.

Starting an Alternate JES2 Subsystem as a Primary Subsystem

You can run an alternate job entry subsystem (JES) as a primary JES in place of the primary JES. To be run as the primary, start the alternate by using the name of the primary, because only the subsystem known to MVS as the "primary JES" can interface with TSO/E. To start the alternate, the procedure used to start the primary must have STEPLIB and HASPPARM DD statements that can be overridden by the START command. If these DD statements cannot be overridden, the desired JES cannot be loaded to replace the primary JES.

To execute a different copy of JES2 as a primary subsystem, one of the following procedures should be used. If the primary member specified at system installation is automatically started, it must be stopped before initialization. You can stop the primary member either by specifying a CONSOLE statement in the JES2 initialization data set or on the MVS START command. Then reply:

```
Rnn,$PJES2
```

when the member prompts you with the \$HASP426 message.

If the primary was not automatically started or was prevented from initializing by the previous procedure, then enter the command S JES2, overriding the data set name and the volume serial on the STEPLIB DD statement to point to the load library containing the alternate subsystem.

The following is a sample procedure that will run either the normal JES2 or any alternate version of JES2 as a primary job entry subsystem:

//JES2	PROC	M=JESAPARM,U=3380,L=LINKLIB,N=SYS1, V=SYSRES
//		
//IEFPROC	EXEC	PGM=HASJES20,TIME=1440
//STEPLIB	DD	UNIT=3380,VOL=SER=&V,DISP=SHR, //
		DSN=&N;.&L;
//PROC00	DD	DSN=SYS1.PROCLIB,DISP=SHR
¹ //HASPPARM	DD	DSN=&SYS1;PARMLIB.(&M),DISP=SHR,UNIT=&U;
//HASPLIST	DD	DDNAME=IEFRDER

Note: Libraries specified in the JES2 procedure must be referred to in one of the following ways:

- Cataloged in the master catalog
- Specify UNIT= and VOL= on the JCL DD statement
- Managed by SMS (UNIT= and VOL= on the JCL DD statement are ignored.)

To cause JES2 to be loaded from an alternate library (TEST.LINKLIB on TSTPAK), and to cause an alternate member of SYS1.VnRnMn.SHASPARM to be used for JES2 initialization, create a member in SYS1.VnRnMn.SHASPARM. Then, enter the following command:

```
S  JES2,N=TEST,V=TSTPAK,M=TESTPARM
```

To make the secondary test JES2 the primary JES2 member once you have finished testing, issue the following MVS command:

```
S  JESA,JOBNAME=JES2
```

This command starts the 'JES2' job as a started task. For more information about this procedure, see "Specifying a Back-up JES2 Cataloged Procedure" on page 25.

Note: JES2 starts each functional subsystem (FSS) through an internal STARTcommand. This command cannot contain variable operands to specify STEPLIB information. If multiple versions of JES2 are maintained in separate libraries, you might need to maintain multiple versions of the FSS cataloged procedure(s) and vary the PROC= keyword of the FSS initialization statements to ensure that the correct version of the HASPFSSM load module is used.

How to Initialize JES2 in a Multi-Access Spool Configuration

It is possible to operate from 2 to 32 members in a MAS configuration, as shown in Figure 3 on page 55. MAS configurations can also participate as nodes in an NJE network. For sample definitions of such configurations, refer to "Multi-Access Spool Configuration Considerations for NJE" on page 309.

The operation of each member in the configuration is independent and includes all functions previously described for single JES2 members. Each JES2 member can:

- Read jobs from local and remote card readers
- Schedule jobs for conversion and execution under MVS initiators
- Print and punch results at local and remote output devices
- Communicate with operators and time-sharing users.

However, all spool volumes are used by all members in the configuration.

The checkpoint data sets in use within a MAS must be shared by all JES2 members. If a checkpoint data set resides on a coupling facility structure, all

members in the configuration must be connected to that coupling facility through the active Coupling Facility Resource Management (CFRM) policy. If the checkpoint data set resides on DASD, the volume containing the checkpoint must be accessible by all members in the configuration.

The members logically share common JES2 job and output queues. The workload can be balanced among members by allowing jobs to execute on whatever member has an idle initiator with the correct setup and required output devices.




Figure 3. Example of a Two-Member Shared JES2 Configuration

Because all members are functionally the same, if one member in the configuration fails, the others can continue processing from the common queue. Only work in process on the failing member is interrupted; this work can be recovered by a warm start of the failing member while other members continue processing. This work can also be recovered by an operator command (\$E MEMBER) from one of the other members, or through the AUTOEMEM option.

Automatic restart management can also be used to restart batch jobs and started tasks (STCs). However, in order for automatic restart management to restart jobs, all JES's must be connected in the same MAS. Although there might be more than one MAS in a sysplex, automatic restart management cannot restart jobs across MASEs. For a description of both recovery methods, see "Recovering from Member Failures on Other JES2 Members" on page 245. For more information about using automatic restart management, see *z/OS MVS Setting Up a Sysplex*.

Accessing JES2 Spool Information in a MAS

JES2 uses shared direct access storage device (DASD) hardware features to access data on all spool volumes. A copy of the JES2 queues and other status information (for example, spool space allocation maps) is written to the checkpoint data set to facilitate a warm start, as with a single JES2 member. This information is available to all members, one at a time, as needed.

Each member in the configuration must have at least one channel path to each spool volume, and these devices must be specified as shared during MVS system installation.

Accessing JES2 Checkpoint Data Sets in a MAS

All members that use the checkpoint data set(s) specified by the CKPTn parameters on the CKPTDEF statement must at least have access to the shared volume on which CKPT1 exists. This shared access ensures adequate workload communication from member to member. JES2 checkpoint access in a MAS configuration depends on whether the checkpoint data set(s) reside on a coupling facility structure or on a DASD volume.

For the checkpoint data set(s) that reside on a structure, the locking capabilities of the coupling facility prevent JES2 members from simultaneously referencing and updating information kept in the checkpoint data set.

For the checkpoint data set(s) that reside on a DASD volume, JES2 processing uses RESERVE and RELEASE logic with a software checkpoint lock to prevent JES2 members from simultaneously referencing and updating information kept in the checkpoint data set. Because of the use of RESERVE, it is recommended that the checkpoint data set not be placed on a spool volume.

For checkpoint data sets residing on DASD, IBM recommends that you add the checkpoint data set(s) to the RESERVE conversion resource exclusion name list (RNL) to prevent global resource serialization (GRS) from limiting access to that data set and degrading performance. For more information about specifying the RESERVE conversion RNL list, see *z/OS MVS Planning: Global Resource Serialization*.

Initializing the Multi-Access Spool Configuration

When setting up a multi-access spool configuration, you must first determine whether your checkpoint data set(s) reside on a coupling facility structure or on a DASD volume. If any of your checkpoint data sets reside on DASD, the VOLUME parameter on the SPOOLDEF statement and the CKPT1=(...,VOL=) and CKPT2=(...,VOL=) parameter specifications on the CKPTDEF statement must specify the same volumes for all members in the configuration. Note that within each member, the spool volume and the two checkpoint volumes must all be separate to reduce any potential loss in the case of volume failure. If checkpoint data sets reside on a coupling facility structure, the CKPT1=(STRNAME=) and CKPT2=(STRNAME=) parameter specifications must be the same for all members in the configuration. In addition, the statements and parameters specified in Table 13 on page 57 must match across the MAS.

Because the default values calculated for the JOENUM= parameter on the OUTDEF statement are configuration dependent, an inconsistency might inadvertently be introduced if this parameter is not specified explicitly at initialization. Although many of the parameters on the SPOOLDEF, OUTDEF, and

NJEDEF statements can be dynamically changed by operator command, several require a warm start or cold start to modify. Review the description of each in *z/OS JES2 Initialization and Tuning Reference* to become familiar with these requirements.

Table 13. Multi-Access Spool and Checkpoint Data Set Compatibility

Keywords	The definition of each of these keywords must be the same on each member in your configuration to allow multi-access spool and checkpoint data compatibility.
CKPTDEF	CKPTn=(({DSN=,VOL=}) (STRNAME=)),INUSE=YES) LOGSIZE=,MODE=
CKPTSPACE DESTDEF	BERTNUM= LOCALNUM= Ndest= RIRMIRMTdest= Udest=
JOBCLASS JOBDEF MASDEF NJEDEF	(all parameters) JOBNUM= XCFCGRPNM NODENUM= OWNNODE=
OUTDEF SPOOLDEF	JOENUM= BUFSIZE= DSNAME= TGSPACE=(MAX=) TRKCELL= SPOOLNUM= VOLUME=

For operational consistency, it is strongly recommended that the installation exit routines be the same in all members. Similarly, values specified on DESTID(jxxxxxxx) and NODE(nnnn) initialization statements should be the same across the configuration, although JES2 will not detect inconsistent values.

IBM recommends that local unit record devices and RJE lines be given unique JES2 device names over the whole configuration. These devices (printers, punches, lines, readers) are defined by JES2 initialization statements; therefore, be certain to define each device in the same manner to each member in your configuration. This allows all devices to be attached to one member (with appropriate manual switching) if other members are not operational.

Similarly, the LINE(nnnn), PRT(nnnn), PUN(nn), and RDR(nn) initialization statements should be set so that a physical device has the same JES2 device number no matter to which member it is attached. For example, if a 3211 printer is one of four local printers on a two-member configuration, it could be initialized as PRT(4) UNIT=102 for one member and PRT(4) UNIT=302 for the other, if it were attached to different channel paths on the two members.

A local unit record device or RJE line can only be attached to one member at any one time. JES2 initialization will detect devices that are not online and place them in a drained state. Later, the device can be activated by entering the \$P device and VARY device OFFLINE commands on the member to which it is attached,

performing hardware switching, then entering the VARY device ONLINE and \$\$ device commands on the new member. The \$\$ command will fail if no hardware path exists.

The algorithm for using the common JES2 queues and other information in the checkpoint data set is determined by the DORMANCY= and HOLD= parameters on the MASDEF initialization statement. These need not be the same for all members in the configuration and should be set according to characteristics such as the number of members in the configuration, relative processor speeds, and response requirements. (Refer to “Part 4. Checkpoint Data Set Definition and Configuration” on page 193 for further information on these parameter specifications.)

Starting the Multi-Access Spool Configuration

Multi-access spool configurations are typically started within a sysplex and as such, are synchronized through the sysplex timer (such as, an IBM Sysplex Timer, 9037). Each JES2 MAS must be entirely contained within one sysplex; including more than one MAS in a sysplex is not recommended. When the installation is not a sysplex, the SYNCTOL= keyword on the MASDEF initialization statement controlled the synchronization of each MAS member to the time-of-day (TOD) clock. But, in a sysplex, the sysplex timer now performs this activity, which renders SYNCTOL= obsolete. JES2 only uses the SYNCTOL= value to ensure that only members of the MAS who have been initialized with the SYNCTOL= value and have contributed to the active checkpoint data set continue to do so. An installation might initialize a JES2 testing member and attempt access to the checkpoint. JES2 uses the SYNCTOL= value to identify and stop this access.

If your configuration is not part of a sysplex then, before starting the configuration, the time-of-day (TOD) clocks on each member should be carefully synchronized with a single time source. Because this synchronization is externally performed and subject to error, the SYNCTOL= parameter on the MASDEF initialization statement specifies the maximum error (in seconds) which JES2 should tolerate. If the synchronization error is greater than SYNCTOL=, then JES2 cannot detect certain illegal operator actions (for example, performing cold start with other members active). However, certain legal operator actions (for example, warm start after member failure) might be disallowed if attempted before SYNCTOL= seconds have elapsed since system failure.

If the synchronization error is greater than the value in the SYNCTOL= parameter value, an attempted NJE connection between members will not be completed and messages and jobs might not flow through the node properly. Small SYNCTOL= values could cause the connection to be broken and remade often, causing undue overhead. SYNCTOL= should be significantly higher than values specified by the DORMANCY= and HOLD= parameters on the MASDEF initialization statement.

Initially, one member of the MAS must do a cold start, other members are added, deleted, or changed on a warm start. As each new member is warm started and initialized, all other members of the MAS are made aware of its existence because each member shares the same spool volumes and checkpoint data sets and communicates through the JES common coupling services (JES XCF).

The individual members (up to 32) of a multi-access spool configuration are specified on the MEMBER initialization statement by the NAME= parameter. Initially, you can define all 32 members of the MAS by defining MEMBER(1) NAME= through MEMBER(32) NAME=. As you require these members within your configuration you can make them available and active by specifying their MASDEF

OWNMEMB= parameter when you start each of the systems. Or you can define each individually at any time on a warm start. On a warm start, members can be added, deleted, or their names can be changed. The following series of examples is provided to illustrate the control you have over your MAS complex with the MEMBER and MASDEF statements. Systematically, the examples are provided to show member definition (**A** and **B**), addition (**C**), change (**D**), and deletion (**E**).

A Defining multi-access spool configuration members:

```

MEMBER(1) NAME=SY01          /* Define member SY01 */
MEMBER(2) NAME=SY02          /* Define member SY02 */
MEMBER(3) NAME=SY03          /* Define member SY03 */
MEMBER(4) NAME=SY04          /* Define member SY04 */
MEMBER(5) NAME=SY05          /* Define member SY05 */
MEMBER(6) NAME=SY06          /* Define member SY06 */
MEMBER(7) NAME=SY07          /* Define member SY07 */
MEMBER(8) NAME=SY08          /* Define member SY08 */
.
.
.
MEMBER(32) NAME=SY32         /* Define member SY32 */
MASDEF OWNMEMB=SY01          /* Define own member */

```

In example **A**, member MEMBER(1) NAME=SY01, defines the first member of a multi-access spool configuration. Each member has been assigned a member name (SY01 through SY32, respectively). If you have defined all 32 possible members to your multi-access spool configuration with MEMBER statements, all available slots in the member ID table will be allotted. You must activate each member by adding that member's name on the OWNMEMB= parameter of its MASDEF statement or the member will not be able to perform any work. When an OWNMEMB= parameter was added to example **A**, only MEMBER(1) was assigned at that time. Therefore, as you start each new member in your MAS, you will need to provide an OWNMEMB= parameter for that member within its initialization stream.

If the OWNMEMB= parameter was not specified, JES2 uses the SMF ID as the default for the OWNMEMB value; JES2 provides a message to inform you that the name will be added. JES2 determines the member number by scanning the MEMBER initialization statements for the OWNMEMB name. If the name is not found, JES2 assigns OWNMEMB to the first available slot in the member ID table.

In the example above, if the OWNMEMB= parameter had not been coded and allowed to default, JES2 would have not found an available member (all slots were allotted in the member ID table) with which to define your member.

You can also use the \$D MEMBER command to verify the status of individual parameters. Two members cannot specify the same OWNMEMB= parameter; the second member ends abnormally. When defining a member, IBM recommends that you explicitly code an OWNMEMB= parameter in the initialization stream of each multi-access spool member.

Following the IPL for the member defined in example **A**, only MEMBER(1) is active, MEMBER(2) through MEMBER(32) are defined but inactive.

Alternately, you can define a single-member MAS with the following initialization statements. (These same statements can be repeated for each member of the MAS, as you typically repeat all other initialization stream statements and modify

them to meet the needs of the particular member. You must, of course, update the MEMBER number and the corresponding name as shown in example **C**.)

B Activate the first member of a JES2 MAS complex:

```
MEMBER(1) NAME=SY01      /* Define SY01          */
MASDEF OWNMEMB=SY01,     /* Define SMF ID for SY01*/
      .                  /* Further define        */
      .                  /* member SY01           */
      .                  /* parameters            */
```

By adding the MASDEF initialization statement with the OWNMEMB= parameter, you have assigned a member name and made that one member active. Other parameter specifications should, of course, be added to this statement to further define the member. (Refer to the MASDEF statement description in *z/OS JES2 Initialization and Tuning Reference* for a complete description of the other parameters.)

At this point, only MEMBER(1) is defined and active, all other members (MEMBER(2) - MEMBER(32)) remain undefined.

To add a second and third member to this single-member MAS add the following initialization statements to their **separate** initialization streams.

C Add a second and third member to this single-member MAS:

INITIALIZATION STREAM FOR MEMBER SY02:

```
      .
      .
      .
MEMBER(2) NAME=SY02      /* Define SY02          */
MASDEF OWNMEMB=SY02,     /* Define SMF ID FOR SY02*/
      .                  /* Further define        */
      .                  /* member SY02           */
      .                  /* parameters            */
```

INITIALIZATION STREAM FOR MEMBER SY03:

MEMBER(2) and MEMBER(3) are defined and added as the second and third

```
      .
      .
      .
MEMBER(3) NAME=SY03      /* Define SY03          */
MASDEF OWNMEMB=SY03,     /* Define SMF ID FOR SY03*/
      .                  /* Further define        */
      .                  /* member SY03           */
      .                  /* parameters            */
```

members of the MAS by specification within their own initialization streams. All other members (MEMBER(4) - MEMBER(32)) remain undefined.

If you need to redefine a member's name this can be done simply by adding the redefined statement, for example:

D Redefine a member's name:


```

MEMBER(3) NAME=MEM3          /* Change MEMBER(3) from */
MASDEF OWNMEMB=MEM3,        /* member SY03 to MEM3 */
.
.

```

You can only redefine a member when that member is inactive. If you attempt to change an active member, JES2 responds with \$HASP876 MEMBER *memname* IS ACTIVE, CHANGE IGNORED.

Because JES2 keeps a copy of the multi-access spool complex configuration in the checkpoint, when you want to delete a member from your multi-access spool complex you must define a null member (refer to the example below); you cannot delete the member by simply omitting the member on a new MEMBER statement.

E Deleting a multi-access spool member:

```

MEMBER(1) NAME=              /* Delete Member SY01      */
MEMBER(2) NAME=SY02          /* Member SY02 still active */
MEMBER(3) NAME=MEM3          /* Member MEM3 still active */
.
.
.

```

As a result of the initialization statement above, MEMBER(1) (defined as SY01) is deleted from the multi-access spool complex. Note that SY01 must be inactive. JES2 performs restart processing for SY01 to allow work on the deleted member to be eligible for restart on other members in the complex. MEMBER(2) - MEMBER(3) (SY02 and MEM3) remain defined and active. MEMBER(1) is now undefined, and MEMBER(4) - MEMBER(32) remain undefined.

Similarly, you cannot change the MEMBERS in a MAS by just changing the name on the MEMBER statement and performing a warm start. This results in JES2 issuing message \$HASP435 MEMBER TABLE PARAMETER ERROR, because the member names you specified already exist in the checkpoint copy.

In order to reassign member names to different processors in a multi-access spool complex, you must:

1. Change the names to temporary identifiers
2. Stop JES2 on all members in the multi-access spool complex
3. Perform an all-member warm start
4. Change the temporary identifies to the desired names
5. Perform another all-member warm start.

For example, a 3-member multi-access spool complex has defined:

- MEMBER(1) NAME=A
- MEMBER(2) NAME=B
- MEMBER(3) NAME=C

The installation now wants to change the configuration to:

- MEMBER(1) NAME=B
- MEMBER(2) NAME=C
- MEMBER(3) NAME=A

Figure 4 on page 62 shows an example of the steps above.

```

MEMBER(1) NAME=A      /* ORIGINAL CONFIGURATION */
MEMBER(2) NAME=B
MEMBER(3) NAME=C
.
.
.

```

Step 1:

```

MEMBER(1) NAME=X      /* DEFINE TEMPORARY      */
MEMBER(2) NAME=Y      /* MEMBER IDENTIFIERS  */
MEMBER(3) NAME=Z      /* AND THEN WARM START */
.
.
.

```

Step 2:
 \$PJES2 on all members in MAS.

Step 3:
 Perform an all-member warm start with the above configuration.

Step 4:
 When JES2 starts redefine with the following statements:

```

MEMBER(1) NAME=B      /* NEW CONFIGURATION   */
MEMBER(2) NAME=C
MEMBER(3) NAME=A
.
.
.

```

Step 5:
 Perform an all-member warm start with the above configuration.

Figure 4. Reassigning Member Identifiers to Different Processors

Job Submission and Queuing

In a multi-access spool configuration, jobs enter the common queue from any input source (local or remote) attached to any member in the configuration. Normally, (unless special actions are taken), jobs are eligible to execute in any member in the configuration just as in a single-member operation. Started tasks and TSO/E users are an exception: they execute only in the member in which they are entered.

There are two different modes of initiators: those owned by JES2 and controlled by JES commands, and those owned and managed by workload management. Whether a job is selected by a JES initiator or by a WLM initiator is determined by the MODE= parameter on the JOBCLASS statement. Initiators from each JES2 member in the MAS select work from the common job queue independently of other initiators on other members of the JESplex. See “WLM Control of Batch Job Initiation” on page 97 for more details.

Job queue entries also contain a member affinity for up to 32 members on the maximum configuration and can contain an independent mode affinity.

Displaying or Updating a Job’s Affinity

Individual jobs can be given affinity to one or more members (less than the total configuration). Member affinity is required if a processor is operating in independent mode; that is, isolated from the complex and only running jobs specifically routed to it. Provide affinity for independent mode by using the SYSAFF= keyword on the

`/*JOBPARM` statement. The `$T` command can be used to give member or independent-mode affinities to all jobs read from a specific input device (local or remote). The `/*JOBPARM` statement overrides the input device default.

If a job's affinity is to specific members in the configuration or to independent mode, the job can be selected only by the members specified and only if the mode of the member (independent or not) matches that of the job.

Member affinity is useful for special processing requirements (for example, emulation) not available on all members of the configuration. Independent mode is useful for testing new components with selected jobs while in a shared configuration.

The display commands (`$DA`, `$DN`, `$DQ`, `$DJ`) can be used to determine (by SMF system ID) the member in which a job is active and the members eligible to process a queued job. The `$T J` command allows you to change affinities of individual jobs or of all jobs with given affinity. The `$T MEMBER` command allows you to place a member in independent mode. The `$D MEMBER` command displays the status of all members in the multi-access spool configuration.

Scheduling Environment

Similar to member affinity, a job may be assigned a scheduling environment to ensure it executes on specific members(s) in the MAS with the `SCHENV=` keyword parameter on the `JOB` statement or using the `$T Job JES2` command. Scheduling environments are installation-defined 16-character names which may be available on any of the MVS systems in the sysplex, or may be available on none of the systems.

JES2 can display the scheduling environment for a specified job, as well as list those jobs waiting for a specified scheduling environment.

SDSF can also be used to display all the scheduling environments defined to the WLM and on which members in the MAS each is available using the `SE` option. The scheduling environment assigned to a job can be update or deleted using the `$T Job` command.

For more information on scheduling environments, see “Job Scheduling Environment” on page 90.

Restarting Jobs

If a member fails, and jobs in execution are recovered and requeued for automatic restart (either by a warm start or the `$E MEMBER` command), those jobs that have journals are given affinity only to the failed member. If the failed member is unavailable, the operator can change affinity with the `$T J` command to attempt restart on another member.

You can also use automatic restart management to automatically restart batch jobs and started tasks (both are considered jobs). If the job is registered with automatic restart management, automatic restart management restarts jobs when either:

- An executing job unexpectedly ends
- The system on which a job is executing unexpectedly ends or leaves the sysplex.

Duplicate Job Names

Duplicate job name protection extends to all members; that is, if one job name matches another job name that is active in execution anywhere in the configuration, the job is temporarily delayed (see the TSO/E section that follows).

By default, JES2 enables duplicate batch job name protection for all members of the multi-access spool configuration. That is, if one batch job name matches another batch job name that is active in execution anywhere in the configuration, the second job is temporarily delayed until the first job completes. You can disable duplicate batch job name protection by specifying `DUPL_JOB=NODELAY` on the `JOBDEF` initialization statement. TSO/E continues to honor this restriction even if you specify `JOBDEF DUPL_JOB=NODELAY` to allow JES2 to concurrently execute duplicate batch jobs with the same name in the multi-access spool configuration.

Priority Aging

Priority aging is done only by the lowest-numbered active member in the configuration.

Output

Printed and punched output processing in a multi-access spool configuration differs very little from that of single-member operation. Member affinity does not apply to selection of work from the job output elements.

The selection of output for a device is governed by a list of work selection (WS) criteria. This list is specified through the `WS=` keyword on the output device initialization statement or through the `WS` operand on the JES2 `$T` command. Either you or the operator can choose from a list of characteristics (user-specified and JES2-specified criteria) to be considered when JES2 selects output for output devices.

RJE

JES2 ensures that the same remote terminal cannot sign on to more than one line anywhere in the configuration at any given time. For dedicated lines, the user must ensure this uniqueness by properly setting line and remote initialization parameters as previously described. JES2 sends a copy of the sign-on message back to the originating remote terminal as an acknowledgement of successful sign-on.

Remote operator messages can be sent across the entire configuration. That is, any remote operator can send messages to any other remote operator (even if attached to different members) and any central operator can send a message to any remote operator.

JES2 sends selected messages generated by remotely submitted jobs back to the remote terminal on which the job was submitted. A multileaving terminal with a console will receive messages on an output printer (not the console) if the terminal was inactive at the time the message was sent, or if the number of messages queued for the terminal exceeds the `RMTMSG=` parameter specification on the `TPDEF` statement.

Configuration considerations for RJE lines are discussed under “Remote Line and Device Configuration” on page 74.

TSO/E

TSO/E user IDs are recognized as job names by JES2 and duplicate job name protection extends across the multi-access spool configuration. Therefore, a TSO/E logon is rejected if a user with the same ID is logged on elsewhere in the configuration. TSO/E continues to honor this restriction even if you specify `JOBDEF DUPL_JOB=NODELAY` to allow JES2 to concurrently execute duplicate batch jobs with the same name in the same multi-access spool configuration.

Jobs submitted by TSO/E can execute anywhere in the configuration, subject to their affinities (as previously discussed). However, held output data sets are accessible (by the TSO/E OUTPUT command) to the submitting user, regardless of where he is logged on or where the job was executed. If you are not using the shared broadcasting function (BROADCAST=NO is either specified on the OUTDEF initialization statement or the default), JES2 processes the NOTIFY messages as requested on the JCL JOB statement as follows:

- If the user is logged on, the NOTIFY message is returned to that user.
- If the user is not logged on, the NOTIFY message is issued on the member from which the job was submitted, and the message is added to the SYS1.BROADCAST data set associated with the originating member. Also, output generated from that job is not available until the originating member has issued the NOTIFY message.

If, however, you are using the shared broadcasting function (BROADCAST=YES is specified on the OUTDEF initialization statement), JES2 processes the NOTIFY message as follows:

- If the user is logged on, the NOTIFY message is returned to that user.
- If the user is not logged on, the NOTIFY could be issued on any member in the complex, and the message is added to the SYS1.BROADCAST data set.

Jobs submitted by TSO/E users can also execute on any configuration in the NJE network. Once a job is successfully transmitted to another node for execution, it is purged at the entry node.

Functional Subsystem Support

The following section provides:

- An overview of what a functional subsystem (FSS) is
- How to use an FSS in a poly-JES environment
- The failure and recovery procedures unique to the FSS address space.

Functional Subsystem and Functional Subsystem Interface

A functional subsystem (FSS) is an extension of JES2 that runs in an address space separate from the JES2 address space. An FSS provides support for a function peripheral to JES2 processing, such as a peripheral device or other component. A functional subsystem application (FSA) executes within the functional subsystem address space and is defined to provide application-specific support to peripheral functions. An FSA allows devices to operate outside of direct JES2 control. The support contained in the FSS/FSA, then, is specific to the task. There is no limit to the number of FSSs that you can define, nor is there a limit to the number of FSAs that you can define to run under an individual FSS.

Note: All FSS-controlled printers, such as the 3820 or 3800-3 operating in full-function mode (no matter how distant the connection), are considered by JES2 to be “local”.

A functional subsystem can be defined to relieve JES2 of device-specific support associated with page-mode data. For example, because page-mode printers have processing requirements not required by line-mode printers (such as translating complex data attributes), the Print Services Facility is an FSS/FSA defined to drive a 3800-3 or 3820 printer when operating in full-function mode.

Because an FSS is common to all FSAs connected to it, the FSS provides a common set of services to those applications. For example, HASPFSSM supports a

number of functions to include acquiring data sets (GETDS) and releasing data sets (RELDs). These functions are invoked from the FSA and are used to communicate with JES2 for data set printing.

Functional subsystems communicate with both JES2 and the FSA that resides within the functional subsystem address space. JES2 communicates with the functional subsystem through the functional subsystem interface (FSI). JES2 supports AMODE(31) callers and data areas across the FSI. JES2 data areas reside in virtual storage, above 16 megabytes. The FSI is not a single definable piece of code; rather an FSI encompasses those individual pieces of code (resident within JES2 and the FSA) that provide the communications between JES2 and the FSA. Figure 5 on page 66 depicts the relationship between JES2 and the functional subsystem components.




Figure 5. Representation of the Relationship between Functional Subsystem Components

Using Functional Subsystems in a Poly-JES Environment

In a poly-JES2 environment (that is, an MVS system in which more than one JES2 is running concurrently) either one or both JESs can start and pass data sets to a functional subsystem for processing (for example, page-mode printing). A functional subsystem is started by an internally produced MVS START command; JES2 processes the START command so that the functional subsystem started task is associated with the appropriate JES2 (the JES2 that processed the START command). A functional subsystem **cannot** communicate with multiple subsystems simultaneously.

Functional Subsystem Recovery Procedures

Processing of page-mode data sets occurs in a functional subsystem address space that is separate from the JES2 address space; therefore, the following two failure or recovery situations can arise:

- The functional subsystem address space abnormally ended.

The functional subsystem attempts to halt the functional subsystem application (FSA) processing or itself through use of its own recovery routines. If the functional subsystem can recover in this manner, JES2 is not aware of the failure. If not, JES2 provides for cleanup of resources, such as the functional subsystem address space, and recovers any work assigned to the failing functional subsystem; all output devices associated with the failing functional subsystem are marked drained.

- JES2 abnormally ended.

When JES2 ends, any started functional subsystem continues to print work assigned to it prior to the JES2 failure. After finishing the assigned work, the functional subsystem becomes idle. After JES2 is restarted (by a hot start), JES2 reestablishes communications with the active functional subsystem and normal processing; that is, assignment of work resumes.

Part 2. Controlling JES2 Processes

Chapter 2. Controlling JES2 Processes	73
Devices	73
Defining Device Configuration	73
Assigning Devices Dynamically After Initialization	73
Remote Line and Device Configuration	74
Network Job Entry (NJE)	75
Remote Job Entry (RJE)	75
Directing Responses to Display Commands	76
Job Submission	76
Internal Reader Facility	76
Defining the Internal Reader Facility	76
Using the Internal Reader Facility	77
JES2 Control Statements that Affect the Internal Reader	79
Performance Considerations for JES2 Internal Reader	79
Card Readers	80
Network Jobs	80
Processing JES2 Control Statements	81
Network Job Transmitter	82
Network Job Receiver	82
Controlling Network Job Headers and Trailer Areas	83
Controlling Network Job Transmitters and Receivers	83
Conversion	83
Pre-Conversion JCL Scan	84
JCL Conversion	84
Scanning the JOB Statement Accounting Field	84
JOB Statement Accounting Field Scan Exit	84
Network Accounting	84
Converter Parameters	85
Defining a Job's Procedure Library	85
Job Selection and Execution	85
The JES2 Job Queue	86
Job Class	86
Job Class Characteristics	86
WLM Classification	88
Modifying Jobs and Classes	88
Job Scheduling Priority	88
Specifying Priority	88
Calculating Priority	89
Member Affinity	90
Job Scheduling Environment	90
Displaying and Controlling Scheduling Environments	90
Duplicate Job Name Control	91
Held Jobs	91
Setting Job Class Limits for Execution	91
Enabling Job Execution Selection	91
Controlling Job Execution Through Exits	91
Controlling the Sequence of Job Execution	92
Serial Job Execution Sequence	92
Concurrent Job Execution Sequence	92
JES2 Control of Batch Job Initiation	93
Operator Control of the Batch Job Workload	94
Using Job Classes with JES2 Managed Initiators	95
JES2 Initiator Attributes	95

Job Priority Aging	96
WLM Control of Batch Job Initiation	97
Controlling Batch Job Selection	97
SMF Recording	98
Considerations for WLM Goals Applied to Batch Jobs	98
The Initiator Cataloged Procedure	99
System Resource Manager Control of the Batch Job Workload	99
Job Monitoring	100
Monitoring the Successful Completion of a Job	100
Entering Commands from a Job Stream	101
Execution Batch Monitoring (XBM) Facility	101
Using the Execution Batch Monitoring Facility	102
Output	103
Default Data Set Characteristics	104
Output Priority	104
Output Priority Aging	106
Output Processing	107
Output Data Set Groups	108
SMF Record Summary: Job-Output Related Information	111
Routing Output to Other Nodes	111
Considerations for Output Produced by APPC Transaction Programs	112
System Data Sets	112
Output Class Assignment	113
Characteristics of Output Classes	113
Blank Truncation	114
Setup Characteristics	114
Demand Setup and Output Data Set Grouping	115
Spin Data Set Processing	115
Spin Data Sets in the NJE Environment	115
System Data Set Characteristics	116
Specifying JES2 Output Size Limits	116
Variable Work Selection Criteria	116
Specifying Work Selection Criteria	117
Determining the “Best” JOE	117
Tuning Work Selection Criteria	121
Output Disposition for SYSOUT Data Sets	124
Specifying Output Disposition	124
Overriding Output Disposition	125
Purging JES2 System Data Sets	126
Offloading and Reloading SYSOUT Based on Output Disposition	127
Transmitting Output to Another Node	127
Automatic Restart Management	127
Dividing Output into Smaller Units	128
Defining Output Limits	129
Considerations for Started Tasks and TSO LOGONs	130
JES2-Provided Client Print Services	131
Printers and Punches	131
Print Chain Alias for 1403 and 3211 Printers	131
3211 Indexing	132
Defining the Advanced Function Printer (Using the PRT(nnnn) Statement)	132
Defining a Functional Subsystem for Advanced Function Printing (Using the FSS(accccc) Statement)	133
Using Advanced Function Printing Printers	134
Compatibility-Mode Support	134
Full-Function Mode Support	134
Creating Output for a 3540 Diskette Writer	135

The JES2 Print Separator	135
Modifying the JES2 Print Separator	137
Creating a JESNEWS Data Set	137
JES2 System Data Sets	139
The JES2 Job Statistics	140
The JES2 Punch Separator Card.	141
Output Routing	142
Routing Data Sets	142
Pooling Remote Devices	142
Specifying Default Output Routing On Input Devices	142
Using Destination Identifiers to Route Output	143
How JES2 Resolves Destinations from Node to Node	147
Origin Node Processing	147
Destination Node Processing	147
Routing Output to Devices at Another Node	150
Avoiding Endless Looping in a Network	151
Specifying TSO/E Userids on a JES2 System	151
Altering Destination Processing Through DESTDEF	152
Preparing Installations to Alter Destination Processing	154
Routing to Multiple Destids	156
Routing to RJE Devices When Rdest=User	156
External Writers	157
Held Job and Data Set Considerations.	157
Defining Held Data Sets	157
Held Output Processing	158
Modifying and Disposing Held Data Sets	158
Offloading Held Jobs and Data Sets	158
Held Data Sets in the NJE Environment	159
Improving JES2 Processing.	159

Chapter 2. Controlling JES2 Processes

This chapter describes the aspects of JES2 processing that you can affect through initialization statements (and their associated parameters) and operator commands. For specific information about coding initialization statements, refer to “Part 1. JES2 Initialization” on page 1. For descriptions of initialization statements, refer to *z/OS JES2 Initialization and Tuning Reference*. For information about operator commands, see *z/OS JES2 Commands*.

Devices

With initialization statements and commands, you can specify the configuration of JES2 local devices, the JES2 internal reader facility, the JES2 remote lines and devices, and the JES2 spool volumes.

Local devices are attached to the MVS system and are used by JES2 for reading jobs and writing output. Local devices include card readers, card punches, internal readers, and printers.

Defining Device Configuration

You identify local devices JES2 uses with the RDR(nn), PRT(nn), PUN(nnnn), and LINE(nnnn) initialization statements. You can also associate JES2 processing parameters with each device, and indicate whether the device is available (started) on completion of JES2 initialization.

During JES2 initialization, JES2 determines the number of printers, punches, and readers by counting each unique PRT(nnnn), PUN(nn), and RDR(nn) initialization statement. JES2 handles any devices not defined during initialization through default parameter values for that type device. *z/OS JES2 Initialization and Tuning Reference* describes the default parameters used.

JES2 dynamically allocates any available local devices, and processing begins on that device when work exists for the device. An operator must start a drained or halted device with a JES2 start command (\$S). During JES2 processing, you start devices with the JES2 start command (\$S device) and deactivate devices with the JES2 stop command (\$P device).

Assigning Devices Dynamically After Initialization

After initialization, operators can use JES2 commands to add, assign, or reassign local printers, punches, readers, communication lines, and channel-to-channel (CTC) adapters. By specifying a device statement without a unit value, the device name and its attributes become known to JES2, but a physical device is not assigned until a unit value is added using a JES2 \$T command. Defining devices in this manner allows installations to dynamically assign or reassign devices after initialization.

You can omit the UNIT= on the following JES2 device initialization statements:

- PRT(nnnn)
- PUN(nn)
- RDR(nn)
- LINE(nnnn)

If you do not specify UNIT= on the PRT(nnnn) statement, JES2 bases the defaults for COPYMARK, FLash, FCB, and UCS on the MODE= parameter. If MODE=FSS,

these parameters default to specifications for a non-impact printer. If MODE=JES, these parameters default to specifications for an impact printer. To determine how JES2 parameters affecting FSS printer characteristics retain values across a hot start, see “Functional Subsystem Reconnection” on page 47.

During initialization, JES2 does not allocate or assign devices defined by these spare device statements. JES2 starts FSS printers with a valid FSS procedure whether or not UNIT= has been specified. After initialization completes, operators can dynamically assign or reassign a physical device by specifying the UNIT= parameter on any of the following commands:

- \$T RDR(nn)
- \$T PRT(nnnn)
- \$T PUN(nn)
- \$T LINEnnnn

Operators can dynamically assign as many local printers through the \$ADD PRT(nnnn) command. However, dynamically assigned devices are saved across a JES2 hot start only.

Notes:

1. To define a device to JES2 permanently, installations must specify a value on the UNIT= parameter in the initialization stream.
2. You must first drain a device before replacing it.
3. You can dynamically add a local printer (JES2- or FSS-managed) using an \$ADD PRT(nnnn) command. You do not need to define spare initialization statements to allow the dynamic addition of printers when using the \$ADD command.
4. If your installation is using Print Service Facility (PSF)* Version 1.4 or an earlier release of PSF, only those local FSS printers that have been defined to the base control program as installation-static can be dynamically assigned to JES2 using \$T commands.

See *z/OS JES2 Commands* for additional information about dynamically assigning or reassigning local devices using \$T commands.

Remote Line and Device Configuration

JES2 supports both NJE and RJE. During JES2 initialization, you should:

- Identify and describe the NJE applications eligible to participate in an SNA NJE network with the APPL(avvvvvv), NODE(nnnn), LINE(nnnn), and LOGON(nnnn) statements.
- Specify the maximum number of concurrent JES2/VTAM sessions allowed with the SESSION parameter on the TPDEF statement.
- If you desire compaction, specify the compaction table or tables you wish to use (with the COMPACT statement).
- Specify which RJE workstation(s) and devices will use compaction (with the RMT(nnnn), R(nnnn).PR(m), and R(nnnn).PU(m) statements).

Note that you can also specify compaction on the \$ADD RMT(nnnn) command and \$T forms of each command listed above.

- Specify the maximum number of nodes (with NODENUM parameter on the NJEDEF statement) in the NJE network to which this JES2 member belongs.
- Identify and specify characteristics for each line, RJE workstation, NJE node and remote device. (By using the LINE(nnnn), RMT(nnnn), NODE(nnnn), R(nnnn).RD(m), R(nnnn).PR(m), and R(nnnn).PU(m) statements.)

Note: If you do not define lines during initialization, you cannot add RJE workstations through the \$ADD RMT(nnnn) command. Also, JES2 sets the RMTNUM= parameter on the TPDEF initialization statement to zero and ignores any RMT(nnnn) initialization statements.

- Specify the number of network SYSOUT and job transmitters and receivers (with the SRNUM=, STNUM=, JRNUM=, and JTNUM= parameters on the NJEDEF or LINE statements) for each NJE line.

You can dedicate (permanently attach) physical and logical (that is, SNA) teleprocessing lines by specifying the line number in the RMT(nnnn) statement that describes the RJE workstation. Any RJE workstation dedicated on a line must use that line for the connection. Any RJE workstation or device that does not have a dedicated line specified can use any line not designated by a RMT(nnnn) statement. This type of line is a nondedicated line.

Network Job Entry (NJE)

JES2 supports communication with remote JES2 complexes with channel-to-channel adapters (CTCAs), binary synchronous communication (BSC), synchronous data link control (SDLC), and system network architecture (SNA) communication facilities. Refer to “Part 5. Network Job Entry (NJE)” on page 255 for a complete description of NJE.

Remote Job Entry (RJE)

JES2 supports both BSC and SNA RJE terminals. Configuring these devices consists of defining RJE workstation facilities, teleprocessing lines, and logical lines for SNA terminals (for example, a 3770, 3790, or a System/32 workstation). The remote configuration can range from one remote terminal (for example, a 2770 or 3780) to an RJE workstation consisting of a system operating many devices. Support of multiple logical units permits the concurrent use of more than one device at an RJE workstation.

You define the devices for an RJE workstation through the RMT(nnnn) statement and the \$ADD RMT(nnnn) command. Use the RMTNUM= parameter on the TPDEF initialization statement to specify the highest number you can define at your installation. If you do not specify this parameter at initialization, it defaults to the highest-numbered RJE workstation defined during initialization. If at initialization, you define an RMTNUM= value and inadvertently then specify an RJE workstation with a higher number, JES2 sets RMTNUM= to the higher value. On both the RMT(nnnn) statement and the \$ADD RMT(nnnn) operator command, you can define up to a maximum of 15 devices as follows:

- **Up to 8 devices** that can consist of a combination of printers, punches, and an optional SNA console. You can define:
 - 1 SNA console
 - Up to 7 printers (or only 6 if you define a SNA console)
 - Up to 7 punches
- **Up to 7 devices** that consist of readers only.

Specifying SETUP=PDIR on either the RMT(nnnn) statement, the \$ADD RMT(nnnn) command, or the \$T RMT(nnnn) command allows you to spool data sets and create multiple copies of output (from a single, transmitted copy).

The RJE workstation operator controls the RJE workstation, the RJE workstation devices, and the jobs submitted through the remote console or the remote card reader. JES2 considers each RJE workstation an extension of the local JES2 facility. For more detailed information about remote devices controlled by JES2, refer to “Part 6. Remote Job Entry” on page 315.

Directing Responses to Display Commands

In some situations, you might want to send the output of a display command to a console other than the one on which the command was issued. For example, in the case of a display command that sends large amounts of output to the console, you might wish to send the output to another console. Use the REDIRECT(vvvvvvvv) initialization statement to redirect the output of a display command from the in-line area of the console on which you entered the command to another console or to another area of the console. For example, the initialization statement,

```
REDIRECT(mastcons) DCONNECT=njecons1-c
```

sends the output of commands that display network connections from the console named **mastcons** to the out-of-line area C of the console named **njecons1**. See *z/OS MVS Planning: Operations* for information on planning and defining consoles.

z/OS JES2 Initialization and Tuning Reference contains a complete description of the REDIRECT initialization statement.

Job Submission

JES2 accepts jobs through:

- Card readers allocated to JES2
- RJE devices allocated to JES2
- NJE job receivers from other nodes in an NJE network in which the local JES2 is a member.
- Offload job receivers
- The JES2 internal reader facility, through which you submit jobs from TSO/E and started tasks (see “Internal Reader Facility” on page 76 for details about the facility).

JES2 queues the jobs submitted to it in priority order. Use the various initialization statements and parameters to control input device characteristics such as input streams, job classes and their attributes, job priorities, whether to initially hold the job, or a job's default performance group. You can change the attributes of jobs coming into this system through the JES2 input service exits 2, 3, 4, and 20. To enable these exits, refer to *z/OS JES2 Installation Exits*.

Internal Reader Facility

The internal reader facility is a logical device similar to a card reader that allows you to submit jobs to JES2. You can also read job streams from tape, disk or any QSAM-supported device through the internal reader to JES2 by using the procedure named RDR. Using the internal reader facility, you can submit jobs from time-sharing logons, started tasks, or other jobs. The ability to submit jobs from currently running jobs or tasks is especially powerful. This ability gives the programmer the flexibility to have a job that reaches a point successfully to submit another job for execution.

Defining the Internal Reader Facility

Define the attributes of the internal reader facility with the INTRDR statement. One of these attributes is the maximum number of jobs that can enter the system concurrently from the internal reader facility. Specify the maximum number (up to 32765) through the RDINUM= parameter of the INTRDR statement.

There are three types of internal readers:

- Batch jobs are submitted by use of INTRDR
- Started tasks are submitted by use of STCINRDR
- TSO logons are submitted by use of TSOINRDR.

The internal readers defined by the RDINUM= parameter on the INTRDR initialization statement are not divided into a fixed number for each type; JES2 varies the number of each type as needed.

All of the internal readers defined by the RDINUM= parameter are available for time-sharing logons and started tasks. They are also available for batch jobs unless BATCH=NO is specified. If BATCH=NO is specified, then batch jobs can be submitted only through real (local) card readers, RJE, NJE, or through spool offload.

Using the Internal Reader Facility

There are 4 methods of using the internal reader facility. These methods are:

- Using a special external writer called INTRDR to submit a job from input in a batch job stream
- Dynamically allocating the internal reader from your program
- Using the IBM-supplied RDR procedure from either a batch job stream or the operator's console to read the job from a QSAM-supported device
- Using the TSO/E SUBMIT command to pass a job stream to the internal reader facility. The MSGCLASS for a job submitted to the internal reader through a TSO/E SUBMIT command defaults to the value specified for the MSGCLASS= parameter on the JOBCLASS(TSU) initialization statement. (For more details about the TSO/E SUBMIT command, see *z/OS TSO/E Command Reference*.)

Submitting to the Internal Reader from Jobs or Tasks: Figure 6 on page 77 shows a step from a job (or task) that submits a job to the internal reader.

```

:
//STEP9      EXEC  PGM=IEBGENER
//SYSPRINT   DD    SYSOUT=Z
//SYSUT2     DD    SYSOUT=(A,INTRDR)
//SYSIN      DD    DUMMY
//SYSUT1     DD    DATA,DLM=XX
//MYJOB1     JOB   ACCT,VAZQUEZ,CLASS=A
//STEP1      EXEC  PGM=CRUSHER
//ERRORS     DD    SYSOUT=A
//INPUT      DD    DSN=JES2.INIT.TUNE,DISP=SHR
//OUTPUT     DD    DSN=SMALL.BOOK,DISP=SHR
XX
//STEP10     EXEC  ...
:

```

Figure 6. Submitting a Job to the Internal Reader

Step 9 writes the JCL that follows the STEP9 SYSUT1 card (up to the XX which acts as a delimiter) to a SYSOUT data set used as input to the INTRDR program.

If the ACB interface was used to open the internal reader, you can use the ENDREQ macro to complete the submission of jobs. For more information about coding the ENDREQ macro, see *z/OS DFSMS Macro Instructions for Data Sets* and *OS/390 IBM Communications Server: SNA Programming*. For more information about JES2 control statement processing, see “JES2 Control Statements that Affect the Internal Reader” on page 79.

Dynamically Allocating the Internal Reader: You can allocate SYSOUT data sets to the special external writer, INTRDR, just as you would any other external writer. For example, your program can issue an SVC 99 (for details on SVC 99, see *z/OS MVS Programming: Assembler Services Guide*) and write JCL-images directly to the internal reader.

When you dynamically allocate the internal reader, the default MSGCLASS for the submitted job is the same as the MSGCLASS of the job or TSO/E logon that submits the job.

Time-Sharing Logon (TSO/E) and Started Task (STC) Flow: Time-sharing logon and started system tasks appear to JES2 as a special form of jobs that are received from designated internal readers. These jobs are queued in special job classes (TSU and STC) and are assigned a MSGCLASS that is set during JES2 initialization [MSGCLASS parameter on the JOBCLASS(TSU) and JOBCLASS(STC) initialization statement].

The time-sharing message class (MSGCLASS parameter on the JOBCLASS(TSU) statement) becomes the output class for all dynamically allocated SYSOUT data sets for which a class is not specified, and becomes the MSGCLASS for all submitted jobs with no MSGCLASS parameter on the JOB statement. It is, therefore, not advisable to set MSGCLASS= to a SYSOUT class that specifies OUTDISP=PURGE. (Refer to “Output Disposition for SYSOUT Data Sets” on page 124 for further information concerning the output disposition of SYSOUT data sets.)

Time-sharing users can dynamically allocate data sets, dynamically deallocate them (spinoff), and print them at the time-sharing terminal (OUTPUT command). JES2 treats a file submitted by the TSO/Extensions interactive data transmission facility as an output data set.

Using the RDR Procedure: Figure 7 shows the JCL procedure IBM supplies for you to use the internal reader to read jobs from tape, disk, or any QSAM-supported device.

```
//IEFPROC      EXEC  PGM=IEBEDIT
//SYSUT1       DD    DDNAME=IEFRDER
//IEFRDER      DD    DSN=NULLFILE,DISP=OLD
//SYSUT2       DD    SYSOUT=(A,INTRDR)
//SYSPRINT     DD    SYSOUT=A
//SYSIN        DD    DUMMY
```

Figure 7. The RDR Procedure

Examples of Using the RDR Procedure: The operator can invoke the RDR procedure to read:

- A job stream from the second file of a tape named JOBTAP on device 180:
S RDR,180,JOBTAP,LABEL=2,DSN=JOBS
- A job stream from a cataloged library of jobs:
S RDR,3330,DSN=PRODUCTN(PAYROLL)
- A job stream starting with a specific job on a tape named JOBTAP, the operator must submit a job to JES2 similar to:

```
//READJOBx JOB ...
// EXEC RDR
//IEFRDER DD DSN=JOBS,VOL=SER=JOBTAP,
// UNIT=3400,DISP=OLD
//SYSIN DD *
EDIT START=JOBx
/*
```

By using conditional JCL, you can cause internal readers to start only under specific conditions. You can then form a dependent job or set of jobs that execute (without operator intervention) only when a master job executes in a desired manner.

For example, to submit BADNEWS only if GOODNEWS does not complete successfully, specify the following:

```
//STEPHEN IF (RC = 0)THEN
/*
//GOODNEWS EXEC PGM=IEBGENER
//SYSPRINT DD DUMMY
//SYSIN DD DUMMY
//SYSUT1 DD JOBS(JOBA)
//SYSUT2 DD SYSOUT=(A,INTRDR)
/*
//STEPELSE ELSE
//BADNEWS EXEC PGM=IEBGENER
//SYSPRINT DD DUMMY
//SYSIN DD DUMMY
//SYSUT1 DD JOBS(JOBB)
//SYSUT2 DD SYSOUT=(A,INTRDR)
/*
//STEPEND ENDIF
```

User-written procedures and programs can further exploit the internal reader facility to select particular jobs, to generate special job streams, and to allow operator submission of production job streams.

JES2 Control Statements that Affect the Internal Reader

The following JES2 control statements affect the way the internal reader handles the input stream it receives.

- /*EOF - ends the current job in the data set and makes it eligible for immediate processing.
- /*DEL - deletes the job in the data set and schedules it for immediate SYSOUT processing. This statement deletes the current job in the job stream. If there is no job in the data set, this statement has no effect. The SYSOUT consists of any JCL submitted, followed by a message indicating that the job was deleted before execution.
- /*PURGE - deletes the job in the data set and schedules it for purge processing. If no job is in the data set, this statement deletes the previous job in the job stream. No output is produced for this job.
- /*SCAN - causes the job to be scanned for JCL errors, but not executed. (The same processing occurs if TYPRUN=SCAN appears on the JOB statement.)

Performance Considerations for JES2 Internal Reader

The following performance considerations can affect performance in a JES2 subsystem.

Use of Unblocked Records for SYSIN and SYSOUT Data Sets: You should not block SYSIN and SYSOUT data sets because the SAM (sequential access method) compatibility interface will increase overhead by unnecessarily deblocking and blocking data sets.

Held Internal Readers in JES2: JES2 treats all internal readers as a single facility, therefore holding one internal reader places all internal readers in hold. This is particularly troublesome when the central operator holds the internal readers and TSO/E users wish to submit jobs. You can avoid this problem by:

1. Assigning a specific job class for all jobs submitted through a particular internal reader. Instead of holding the internal reader, you can hold the class by using either a JES2 initialization statement or a JES2 \$T JOBCLASS(x),QHOLD=YES command.
2. Use the TYPRUN=HOLD parameter or TYPRUN=JCLHOLD parameter on the JOB statement.
3. Submitting the job through an internal reader and individually hold it with the JES2 \$H J command.

RDINUM= Parameter Specification on the INTRDR Statement: You should make sure that you specify the RDINUM= parameter on the INTRDR statement large enough to prevent jobs waiting for an available internal reader.

There is no method to determine which jobs will use the available internal readers. However, you can control whether JES2 uses internal readers defined through the RDINUM= parameter exclusively for time-sharing logons (TSOINRDR) and started tasks (STCINRDR) or for batch jobs as well.

The RDINUM= parameter specifies the number (0-32765) of internal readers. Internal readers defined through this parameter are dedicated exclusively to time sharing LOGONS and started tasks when BATCH=NO is specified on the INTRDR statement. When BATCH=YES is specified, internal readers can also be used to process batch jobs.

JES2 always provides two more internal readers in addition to those defined through the RDINUM= parameter (one dedicated exclusively to time-sharing LOGONS and one dedicated exclusively to started tasks); this specification cannot be changed by this or any other JES2 parameter. JES2 returns the value specified on this parameter in response to a \$D INTRDR command.

Because jobs can allocate internal readers, the possibility exists that JES2 will force jobs to wait because of a lack of internal readers available to process the work. The JES2 default for this parameter is 2.

Card Readers

JES2 automatically starts local card readers if you specify the START=YES parameter on the RDR(nn) JES2 initialization statement. The operator can then enter job streams into the system by placing the cards in the hopper and pressing the start button on the reader; the operator does not have to issue a JES2 start (\$S) for the reader. The operator deallocates the card reader from JES2 by issuing the JES2 stop (\$P) reader command.

Network Jobs

In the NJE environment, you can pass jobs read into the system through the input service processor to other host nodes in the network for execution service. The

input service processor treats jobs you want processed at other nodes in the network the same as jobs you wish executed locally. This allows JES2 to determine the node of execution at any time during the scheduling process.

You can route job output from one node to another by:

1. Specifying a symbolic destination identifier on the following:
 - The `/*ROUTE PRT` JES2 control language statement
 - The `/*ROUTE PUN` JES2 control language statement
 - The `DD JCL` statement,
 - The `OUTPUT JCL` statement.
2. Using the same symbolic destination identifier as the subscript of the `DESTID(jxxxxxxx)` initialization statement.

For example, if Node 1 uses a symbolic, `PRTBIG`, to define a printer on Node 2, NODE 2 can change that printer in the future from remote 7 to remote 8 by specifying `R8` on the `DEST=` parameter without having to advise Node 1 of the change.

At NODE 1, this is the `DESTID(jxxxxxxx)` initialization statement,
`DESTID(PRTBIG) DEST=N2.PRTBIG`

At NODE 2, this is the `DESTID(jxxxxxxx)` initialization statement,
`DESTID(PRTBIG) DEST=N2.R7`

Processing JES2 Control Statements

The input service processor also processes the `/*XEQ` control statement, `/*ROUTE XEQ` control statement, and `/*XMIT` control statement. JES2 converts the execution node specified in any of these control statements to a node number or specified userid, replacing the default (or previously specified) node number.

You can send jobs for execution on a guest virtual machine on a VM node by specifying a symbolic destination defined on a JES2 `DESTID(jxxxxxxx)` initialization statement. If you do not specify a symbolic destination, JES2 processing moves the second-level route code from the `/*XEQ` or `/*XMIT` JECL statement. VM uses the execution userid as the destination virtual machine for the jobs it receives.

If the execution node number does not match the input node, JES2 will not process any execution-related control statements. JES2 processes JES2 control statements on the input node and the execution node when they appear before the `/*XEQ` (or `/*ROUTE XEQ`) control statements. If you place the `/*XEQ` (or `/*ROUTE XEQ`) statement before other JES2 control statements, JES2 processes only the `/*MESSAGE` and `/*SETUP` control statements at the input node if they come before the `/*XEQ` statement. All other control statements are **not** processed until they reach the execution node.

Execution-related control statements include the following JES2 control statements:

- `/*MESSAGE`
- `/*SETUP`
- `/*ROUTE` (PRINT and PUNCH)
- `/*JOBPARM`
- `/*OUTPUT`

Use the `/*XMIT` control statement to submit data into the network. The transmitter considers all data following an `/*XMIT` statement, up to a delimiter statement as one network job. The delimiter statement defaults to `/*`, but can be changed through the `DLM=` parameter on the `/*XMIT` JES2 control language statement. For information about specifying this delimiter, see the *z/OS MVS JCL User's Guide*. The network job is transparent to all nodes but the receiving node.

Network Job Transmitter

A network job transmitter selects jobs from the job transmission queue. If there is a network job header and trailer, (the job has been received from a node other than the node where the job was created), the job transmitter updates them as appropriate. For example, if the job was destined for execution at this node but routed to another node (through either a `$R` operator command or a `/*XMIT` control statement), the job transmitter places the new job card information in the job header. If the job was received from the origin node, the job transmitter builds the NJE headers and trailers so that the job can be sent across the network.

The job transmitter sends the job exactly as the system read it in. The transmitter does not send any statements added by the local input service processor and recovers, for transmission, any statements which the input service processor deleted or modified. Because JES2 preserves the original job stream on the spool disk, the job transmitter can reconstruct the original job.

You can store job-related information with both job and SYSOUT data sets, and transmit installation-specific data from node to node using the `$JCTX` and `$NHD` services. See sample exit `HASXJECL` in the `AHASSAMP` JES2 distribution library. For more information about using these services, refer to *z/OS JES2 Macros*.

Network Job Receiver

The network job receiver component, which receives jobs over the NJE lines, is similar to the input service processor. The network job receiver reads in jobs from other host nodes in a manner similar to the method used to read in jobs from RJE workstations. The difference is the network job receiver expects NJE protocols from the other host nodes and there are some changes to job processing. When the receiver detects a job destined for another node, it reads the job in to the spool without examining the data. The node then uses the network job transmitter to continue the job's journey to the ultimate destination.

When a node receives a job from the network, JES2 uses the header and trailer it receives from the network job transmitter. If the received job header or trailer does not contain all the sections necessary for JES2 processing, JES2 adds them to the headers received. The JES2 input service processor treats multiple jobs received in a single file as a single job. Sending multiple jobs through the network in a single file could cause unpredictable results; a job might execute at a node other than the one you intended.

Identifying Jobs Received From the Network: When a node receives a job from the network, the node attempts to assign the job identifier (JES2 job number) that appears in the jobheader, if the identifier is not in use. If unable to use the original job identifier, the input service processor assigns a new number as if the job entered the system on a device attached to the executing processor. However, the input processor does not replace the job identifier that appears in the job header. The original job identifier remains in the job header and remains with the job as it progresses through the network. (You can exercise some control over the job identifiers by using the `RANGE=` parameter on the `JOBDEF` initialization statement.)

After the node receives the job, the input service processor queues the job for either JCL conversion or job transmission, depending on the value of the execution node in the job header. If the execution node in the job header matches the node identifier of the node that received the job, the input service processor queues the job for execution. If the execution node does not match, the job continues through NJE lines until the job reaches the execution node specified in the network job header.

Data previously spooled without examination (for example, data transmitted with a /*XMIT statement or data spooled for transmission at an intermediate node), and rerouted locally must again go through input service processing. A logical route transmitter and route receiver reroute network jobs to the local node.

Controlling Network Job Headers and Trailer Areas

Installations can enhance the performance of their JES2 members by controlling the amount of storage allocated for NJE headers and trailers through the HDRBUF= parameter on the NJEDEF initialization statement. The HDRBUF= parameter allows you to specify the number of cells allocated at initialization through the LIMIT subparameter. Use this subparameter with great care; specifying too small a value could decrease member throughput by creating resource contention for the headers and trailers.

Consider the number of jobs actively transmitted or received by your installation at one time when setting this parameter. For most installations, the JES2 default provides enough cells for NJE headers and trailers.

However, if your installation transmits many small jobs (100 lines or less) across multiple active NJE lines, JES2 transmits headers more frequently and might need a larger number of buffers. One sign that indicates your installation requires a larger LIMIT value is a shortage of virtual storage. For the exact specifications of this parameter, see *z/OS JES2 Initialization and Tuning Reference*.

Controlling Network Job Transmitters and Receivers

Control the number of network job transmitters and receivers associated with each NJE line by specifying the JTNUM= and JRNUM= parameters on the NJEDEF statement. Use the STNUM= and SRNUM= parameters on the NJE statement to control the number of SYSOUT transmitters and receivers associated with an NJE line. The values specified for these parameters are related (see *z/OS JES2 Initialization and Tuning Reference*, for coding restrictions).

Job Transmitter Selection: The NJE job transmitters select files destined for nodes reachable through the NJE line with which they are associated. Job transmitters select files from the transmission (\$XMIT) queue, which is ordered FIFO (first-in-first-out) within priority. You can specify multiple transmitters (and receivers) for a line as described in “Specifying Transmitters and Receivers” on page 276. You can specify work selection characteristics for job transmitters as well as for SYSOUT transmitters.

Conversion

The converter routine processes the JCL for a job, logon, or started task and converts the JCL into converter/interpreter text. The job is then available for execution, which occurs as soon as an initiator eligible to process the job is available.

Pre-Conversion JCL Scan

The JCLERR parameter on the JOBDEF initialization statement sets the conditions under which JCL scan errors cause job termination prior to conversion.

The pre-conversion scan is only for JOB, DD *, and DD DATA statements. If the job ends on a JCL error at this point, there is no guarantee that other JCL errors do not exist. If the job is not ended on a JCL error at this point in the process, it might still fail on a JCL error during conversion.

JCL Conversion

Unless you hold a job, it is eligible for JCL conversion as soon as JES2 places the job on the queue. Invoked for every job, the converter receives converter parameters and a pointer to a cataloged procedure library from JES2.

You can enable Exit 6 to scan and change the Converter/Interpretext. Refer to *z/OS JES2 Installation Exits* for information about Exit 6.

Scanning the JOB Statement Accounting Field

Use the ACCTFLD= parameter on the JOBDEF statement to control whether JES2 is to scan the accounting field of the JOB statement. The accounting field is valid if its format matches the format specified for JES2. (For a description of the JES2 format for the accounting field, see the accounting field parameter described in *z/OS MVS JCL Reference*.)

JOB Statement Accounting Field Scan Exit

You can supply an Exit 3 installation exit routine to scan and change the accounting field in the JOB statement. See *z/OS JES2 Installation Exits* for information about Exit 3 and for the exit routine's relationship to the ACCTFLD= parameter on the JOBDEF initialization statement.

Network Accounting

JES2 recognizes the following network accounting control statement:

/*NETACCT=vvvvvvvv

where vvvvvvvv is a 1- to 8-byte alphanumeric character network account identifier. When the input service processor (HASPRDR) encounters this statement, it inserts the network account identifier in the job's job header and looks up the number in the network account table built at JES2 initialization, to find an associated local account number. If a local account number is found, it is moved into the job's job control table, overriding any account number present in the JOB statement. HASPRDR always interprets the /*NETACCT statement, regardless of its position in relation to the /*ROUTE XEQ or /*XEQ statement.

When transmitting a job or its system output, JES2 sends the network account number as part of the job header. At each node, the job receiver and SYSOUT receiver perform the same table lookup that HASPRDR did to obtain a local account number for use by that node. Thus, accounting is a local function using whatever set of account numbers the system programmer defined on a given node.

The JES2 NETACCT initialization statement determines the correspondence between the network account numbers and the local account numbers for a node. JES2 uses the parameters on the NETACCT statement to build the network account table used by HASPRDR, the job and SYSOUT transmitters, and the job and SYSOUT receivers.

Converter Parameters

The JOBCLASS(v) initialization statement contains parameters that define an installation's defaults for converter parameters. If you do not specify the converter parameters, JES2 assigns its own defaults during initialization processing. The converter parameters you can affect include; estimated execution time, JCL and allocation MSGLEVEL options, command disposition and authority, and bypass label processing options. Refer to *z/OS JES2 Initialization and Tuning Reference* for descriptions of the specific parameters.

Defining a Job's Procedure Library

SYS1.PROCLIB contains the JES2 cataloged procedure. This procedure defines the job-related procedure libraries. Figure 8 is an example of defining procedure libraries. All the libraries reside in the system's master catalog.

```
//PROC00 DD DSN=SYS1.PROC1,DISP=SHR
//PROC01 DD DSN=SYS1.PROC2,DISP=SHR
...
//PROCnn DD DSN=SYS1.LASTPROC,DISP=SHR
//anyname DD
```

Figure 8. Specifying Procedure Libraries in the JES2 Procedure

The procedure library a job uses depends on the value of the PROCLIB= parameter on the JOBCLASS(v) initialization statement. Programmers can override the default specification by specifying a /*JOBPARM PROCLIB= statement in their JCL, and coding the name of the DD statement in the JES2 procedure that points to the library they want to use. For example, a programmer is running a job in class A. That class has a default PROCLIB of SYS1.PROC1. The programmer wants to use a procedure that resides in SYS1.LASTPROC. That programmer would include a /*JOBPARM PROCLIB=PROCnn in the JCL.

Another way to specify a procedure library is to use the JCLLIB JCL statement. See *z/OS MVS JCL Reference* for more information on the JCLLIB statement.

Any library that you will specify in initialization statements must have a name in the PROCnn form in the JES2 procedure. Other procedure libraries might have any DD name that follow the general rules for DD statements. If you require multiple data sets for one DD name, specify those data sets as concatenations in the JES2 cataloged procedure.

If the procedure library is not specified or specified and not found, PROC00 is used.

Job Selection and Execution

Jobs exist to be read in, converted, classified, and ultimately run. Many factors can affect how, where, when, and if they will run, such as:

- Job Class
- Control of Initiators by JES2 or WLM
- Job Selection Priority
- Job Hold Status
- Member Affinity
- Scheduling Environment
- Job Name
- Number of other Jobs queued for Execution
- Configuration of Active Initiators

- Workload Manager Policy

This section describes each of these factors and how they influence job flow during the execution phase.

The JES2 Job Queue

JES2 receives a job, places its JES2 control blocks on spool, and creates a job queue entry (JQE) on the JES2 job queue. JES2 uses a job queue index (JIX) based on the job number to more efficiently access the jobs on spool.

The queue entry for each job contains the job name, job priority, the IDs of the entry and execution nodes, a flag that indicates the held status of the job, pointers to JES2 control blocks on the spool, and the next JES2 process for which the job is eligible (transmission to another node in an NJE network, JCL conversion, execution, output processing, purging).

Batch jobs are selected for execution by initiators, each one running in a separate address space. Initiators are controlled by JES2 or by MVS workload management (WLM). Who controls the initiators is determined by the job class and by the `MODE=` parameter (JES or WLM) on the `JOBCLASS` statement. JES2 maintains two different queue organizations for all jobs awaiting execution to service the two different selection mechanisms:

1. All jobs are queued by job class, priority, and the order in which they finished conversion. This is the queue from which JES2 managed initiators select jobs for execution. See “JES2 Control of Batch Job Initiation” on page 93 for more details.
2. Jobs awaiting execution in WLM managed job classes are also queued by their WLM assigned service class in the order they were made available for execution. This is the queue from which WLM managed initiators select jobs for execution. See “WLM Control of Batch Job Initiation” on page 97.

Started tasks and Time Sharing Users do not need initiators to begin execution. They are not affected by workload management nor other jobs in the queue but are initiated immediately by JES2.

Job Class

There are 38 classes of jobs possible under JES2. The system reserves two for its use: STC for started task control, and TSU for time-sharing logons. The other 36 classes, A-Z and 0-9, are for normal batch jobs and you use them to help control the job mix. The `CLASS=` keyword on the `JOB` statement identifies the execution class for the job. If not coded on the `JOB` statement, the class associated with the particular device that the job entered the system on becomes the job's execution class. The `INTRDR` initialization statement defines a logical device for jobs entering the system through the internal reader facility.

There are no absolute rules for assigning job classes, and some experimentation is necessary.

Note: The `CLASS=` keyword on the `JOB` statement is ignored for started task jobs.

Job Class Characteristics

During JES2 initialization, you can assign job characteristics to jobs queued in each class to determine:

- A default performance group for each job.
- JCL conversion parameters.

- Whether to initiate jobs in this class by JES2 managed initiators or WLM managed initiators.
- Whether to impose limits on the maximum number of jobs that can be in execution at one time in the MAS.
- Whether to hold jobs in this class after conversion.
- Whether to copy jobs in this class directly to the message class output, without undergoing conversion or execution.
- Whether to convert the job and queue for output without execution.
- Whether to produce a JES2 job log for jobs in this class. (The JES2 job log is a list of all messages and replies issued by, or on behalf of, a job.)
- Whether to save a job journal for jobs in this class. If you use checkpoint restart or restart a job step, you need to save the journal or the system can not automatically restart the job if it fails or if there is a system restart.
If you use automatic restart management to restart a job, you do not need to save the journal because automatic restart management of MVS does not use the job journal when restarting jobs.
- If execution batch monitoring facility jobs can run in this class.
- Whether to suppress output for jobs in this class (for example, started tasks).
- The procedure library (PROCnn) definition.
- SMF options.
- If the system can restart this job in the event of a JES2 warm start.

When first creating your initialization data set(s), you can define a “universal” job class statement and specifications. Define `JOBCLASS(?)` as a single `JOBCLASS` statement; it provides a “universal” set of characteristics for **all** 36 job classes. (The ‘?’ wild-card character refers to the one-character job classes, as opposed to ‘**’ which would include the ‘STC’ and ‘TSU’ classes.) Then add specific `JOBCLASS(v)` statements after this statement for those classes that require individual specification.

JES2 overrides previously-defined initialization statements with duplicates of the statement it reads later in initialization processing. In this manner, only specific `JOBCLASS(v)` statements override their “universal” `JOBCLASS(?)` or `JOBCLASS(*)` specification and the “universal” characteristics remain valid for all other “non-specifically” defined classes.

For example, in the following initialization statements:

```
JOBCLASS(?) AUTH=IO,MSGLEVEL=(1,1),PERFORM=10
:
:
JOBCLASS(X) AUTH=INFO,IEFUSO=NO
```

Job class X overrides the previous value of `AUTH=IO` with `AUTH=INFO`, and the `IEFUSO` value (which defaulted to YES) is changed to NO. Job class X uses the values for `MSGLEVEL=` and `PERFORM=` from the `JOBCLASS(?)` statement.

A default `SCHENV` can be specified for each `JOBCLASS` (not for `JOBCLASS(STC)` or `JOBCLASS(TSU)`). This value will be provided each job at the end of JCL conversion provided that a `SCHENV` has not already been associated with the job. A `SCHENV` can be associated via the user specifying `SCHENV=` on the `// JOB` statement or via JES2 installation exits which occur before the end of conversion.

Jobs are assigned to JES2 or WLM managed initiators based on the MODE parameter on the JOBCLASS statement. JES2 and WLM initiators select jobs using different criteria:

- JES2 uses job class and scheduling priority as selection criteria. See “JES2 Control of Batch Job Initiation” on page 93 for details.
- Workload management uses service class as selection criteria. See “WLM Control of Batch Job Initiation” on page 97 for details.

Note: All JOBCLASS parameter definitions are MAS-wide, and can only be changed with an operator command or a JES2 cold start.

WLM Classification

JES2 uses workload management classification services to assign a service class to each job after it is converted, regardless of its job class. The service class is assigned based on WLM rules which can include attributes such as Job Class, Job Name, Job Priority, Userid, Job Accounting Information, and PERFORM= specification on the JOB statement. See *z/OS MVS Planning: Workload Management* for details.

You should take care not to classify both JES2 managed classes and WLM managed classes into the same service class. Workload management may not be able to effectively meet its goals if some jobs are initiated through JES2 and others through the WLM.

Modifying Jobs and Classes

JES2 allows each installation to further control batch jobs by allowing you to:

- Switch job classes between JES mode and WLM mode with the \$T JOBCLASS,MODE= command.
- Change the job class, or priority of a particular job with the \$T Job command. (JES2 will call WLM to re-classify the job.)
- Modify the service class of a batch job with the JES2 \$TJob,SRVCLASS= operator command.

Any of these actions may change the service class or scheduling characteristics of the job. For more information, see the JOBCLASS(v) statement in the *z/OS JES2 Initialization and Tuning Reference*, and the \$T JOBCLASS and \$T Job statements in the *z/OS JES2 Commands*.

Job Scheduling Priority

The priority on the /*PRIORITY statement determines the job's scheduling priority for JES2 managed initiators. If not specified, JES2 calculates this priority based on estimated execution time and the JOBPRTY(n) initialization parameters. You can increase the priority with the PRIOINC parameter up to the PRIOLIM limit on the RDR(nn), Rnnnn.RD(m), or INTRDR initialization statements.

Jobs in JES2 controlled job classes are queued FIFO within priority within job class. Priority is not used directly to order jobs in WLM managed classes, but can be used as a criteria for determining service class.

Specifying Priority

Specify priority on the /*PRIORITY statement if you have coded PRTYJECL=YES on the JOBDEF initialization statement (or allowed the parameter to default). If specified, the /*PRIORITY statement must immediately precede the JOB statement, or JES2 flushes the input stream until it finds another JOB or /*PRIORITY statement. You can also specify priority by using the PRTY= keyword on the JCL

JOB statement provided PRTYJOB=YES appears on the JOBDEF statement of the initialization stream you used to initialize JES2.

Calculating Priority

When a /*PRIORITY or PRTY= on the JOB statement do not specify the scheduling priority, JES2 calculates the priority from the estimated execution time. Supply these estimates through the: /*JOBPARM statement, the accounting information on the JOB statement, or the ESTIME initialization statement.

To calculate priority, JES2 uses the PRIORITY= and TIME= parameters on the JOBPRTY(n) initialization statement as a table of values. You can supply these values on the JOBPRTY(n) statement or allow them to default. The following example uses the default values to calculate priority:

Table 14. Priority Table Example

If TIME<=*	Then JOBPRTY(n)=	Then PRIORITY=**
2	(1)	9
5	(2)	8
15	(3)	7
279620	(4)	6
.	.	.
.	.	.
.	.	.
279620	(8)	2
279620	(9)	1

* The TIME values are estimates of the number of minutes a job requires to execute.

** These are the defaults for corresponding n values. For example, if you specify TIME= to estimate 4 minutes execution time,

4 minutes implies n=2 and n=2 implies PRIORITY=8

If the job is placed on the HARDCOPY queue, JES2 ignores the job priority (for example, 8, as calculated in the above example); the actual priority used (in this example) is the output priority.

By specifying other values for the tables (during JES2 initialization), you can more closely control your installation's priority assignments. If you build your own priority table based on estimated execution time, be certain the values that you supply appear in ascending order (as are the values in the default table in Table 14 on page 89). The order is important because JES2 uses the TIME= values in a "less than or equal to" order when calculating a priority that does not exactly match the values in the table.

For example, in Table 14 on page 89, if you submitted a job with an execution time of 10, JES2 calculates n as 3 because 10 is less than or equal to 15. If the estimated execution time is 16 to 279620, n is 4. You can use n values 4 through 9 to further control your installation's priority requirements.

Note: Values specified on the JCL /*JOBPARM statement override those in the accounting field of the JOB statement.

During JES2 initialization, you can specify the ACCTFLD parameter on the JOBDEF initialization statement and cause JES2 to ignore the accounting field on the JOB statement.

Member Affinity

In addition to using job classes and initiator selection, batch jobs can specify which members in the MAS can process them by explicitly coding the member names on the SYSAFF parameter of the /*JOBPARM statement in their JCL. The member IDs are explicitly specified through this mechanism. You can modify the member affinity of a batch job with the \$TJob,SYSAFF= command.

Job Scheduling Environment

Similar to but independent from member affinity, a job may also be assigned a “scheduling environment” to ensure it executes on the members in the MAS which have the required resources, or specific environmental states. The states may be associated with hardware resources such as a vector facility, an address space such as DB2, or an abstract state such as time of day (shift) or day of the week. The environment can be specified with the SCHENV= keyword parameter on the JOB statement, or through an installation exit. They can also be assigned via a JOBCCLASS default or using the \$T Job JES2 command. Scheduling environments are installation-defined 16-character names which may be available on any of the MVS systems in the sysplex, or may be available on none of the systems.

Use workload management to define the scheduling environments and make them available or unavailable on each system, based on the “ON” or “OFF” state of resources.

The scheduling environment is validity-checked by the converter and must be defined to workload management, or else the jobs will fail with a JCL error. JES2 detects the availability of scheduling environments on each member, and allows an initiator to select jobs only if the specified scheduling environment is available. This is true for both JES2-managed initiators and WLM-managed initiators. In addition, any member affinity specified through the SYSAFF= parameter as well as the job class and initiator class must match.

For more information on the definition and control of scheduling environments, please see *z/OS MVS Planning: Workload Management*.

Displaying and Controlling Scheduling Environments

JES2 can display the scheduling environment for a specified job, as well as list those jobs waiting for a specified scheduling environment. Use the \$DJnnnnn, LONG command to display the environment specified for the job, or \$DJOBQ, SCHENV=env_name to display jobs waiting for a specific scheduling environment. In addition, you can display why a job will not run with the DELAY parameter, in which the reason might be because the scheduling environment (SCHENV) is not available.

Once a scheduling environment is assigned to a job, you can change it or remove it using the \$T Job JES2 command.

SDSF Options: You can display the job scheduling details about specific jobs with the “Job Information” pop-up on the job input (I) panel. You can also display all the scheduling environments defined to the WLM and on which members in the MAS each is available using the SDSF “SE” option.

In addition, authorized SDSF users can display and set the state of various resources on each member using the “RES” option.

Refer to *SDSF Guide and Reference* for specific SDSF information.

SMF Recording: To help you monitor and manage the scheduling environment, SMF type 26 and 30 records have been expanded to include the scheduling environment name.

See *z/OS MVS System Management Facilities (SMF)* for details.

Duplicate Job Name Control

By default, JES2 enables duplicate batch job name protection for all members of the multi-access spool configuration. That is, if one batch job name matches another batch job name that is active in execution anywhere in the configuration, the second job is temporarily delayed until the first job completes. You can disable duplicate batch job name protection by specifying DUPL_JOB=NODELAY on the JOBDEF initialization statement.

CAUTION:

If you specify DUPL_JOB=NODELAY, jobs with the same job name may run concurrently with adverse effects. Make certain that this serialization mechanism is not being used in your environment before changing this parameter.

Held Jobs

JES2 does not remove a held job from the queue; instead JES2 marks the job ineligible for selection. You can hold a job at any time. Thus, when an operator holds a job in execution, the job is not eligible for output processing until the operator releases it. You can hold a particular job, a job class, or all jobs.

If you specify TYPRUN=HOLD on a JOB statement and then transmit that job through the network, the execution node holds the job after conversion of the JCL. If the job card specifies TYPRUN=JCLHOLD, the entry node and each of the destination node(s) holds the job.

Setting Job Class Limits for Execution

You can limit the number of jobs in each class that can execute simultaneously in the MAS by using the XEQCOUNT=MAXIMUM= parameter on the JOBCLASS statement. This applies to JES2 and WLM managed job classes, and can be altered with the \$T JOBCLASS command. There is no facility to control the number of jobs in execution by class on an individual system basis.

Enabling Job Execution Selection

You can stop or start the selection of batch jobs by JES2 or WLM managed initiators on an individual system with the \$P XEQ or \$S XEQ command.

The initial setting when JES2 first initializes is to allow selection. If you want to prevent this, place a \$P XEQ command in your JES2 initialization deck.

Controlling Job Execution Through Exits

You can alter the characteristics of a job through the following exits:

- Exit 2 for JOB statement scan
- Exit 20 for end-of-job-input processing

- Exit 6 for converter/interpreter text

SMF exit IEFUJV can also change the job's scheduling attributes.

Once jobs are queue for execution, you can also use these JES2 exits to control the job selection:

- Exit 14 for JES2 managed initiators only (do your own job selection)
- Exit 49 for both JES2 and WLM managed initiators (accept or reject the selected job)

Refer to *z/OS JES2 Installation Exits* for information about these exits.

Controlling the Sequence of Job Execution

Because multiple JES2 subsystems alter the execution queues in a shared-spool environment, jobs in the same class with the same priority can execute out of their reader (job number) sequence. You should be aware of the how various job stream environments are affected by this execution out of sequence and the steps you can take to control the execution sequence.

Serial Job Execution Sequence

If you define in the PCEDEF initialization statement that your MAS is to have only one converter processor (CNVTNUM=1), then you force the JES2 system to convert and execute jobs in the order of their reader (job number) sequence. Although this setup controls the order of job conversion and execution, it has the following implication and disadvantages:

- JES2 is limited to processing your workload in a serial manner without respect to the types of jobs that are being submitted. Large batch jobs and TSO logons are treated in a similar way.
- Each of the job's resources are required when the job executes. As such, any migrated libraries and data sets that the job needs, must be restored before the job can execute. The time spent waiting for these migrated resources can backup other jobs in the queues.
- System hangs and deadlocks can occur in the system. When jobs are waiting for resources that have been migrated, the migration program needs to run and restore these resources. The migration program is often a job that needs JES2 conversion prior to it running. Since only "1" JES2 converter processor is defined to do the conversion and it is waiting, the migration cannot occur and the system becomes deadlocked. As an example, this condition can occur for jobs that need JCLLIB data sets, which have been migrated by a product like DFHSM.
- If a job has an exclusive ENQ on a JCLLIB data set and another job needs that JCLLIB data set, the job must wait till the ENQ is released.

Concurrent Job Execution Sequence

If you define in the PCEDEF initialization statement that your MAS is to have more than one converter processor (CNVTNUM=2, which is the default, or CNVTNUM > 2), then concurrent JES2 converter job processing can take place. However, this concurrent processing does affect the sequence of job execution. Two or more jobs with the same class and the same priority can be in conversion processing at the same time. Whichever job finishes conversion first is then queued for execution first, regardless of the order in which the job was submitted. You need to consider the following implications when setting up your system with CNVTNUM=2 or CNVTNUM>2:

- JES2 conversion processing occurs in different ways depending on whether the conversion processor represents an "even" (2,4,6, etc.) or "odd" conversion

processor (3,5,7, etc.). As an example, for CNVTNUM=5, you define "3" odd conversion processors (1,3,5) and "2" even conversion processors (2,4). An even-numbered processor continually processes jobs through JES2 conversion and does not wait. An odd-numbered processor waits for a job's resources to become available.

Odd-Numbered Conversion Processing

Odd-numbered conversion processing waits for the resources to be available. When the resources become available, conversion continues.

There are two primary conditions that affect JES2 conversion processing:

1. JCLLIB data sets need to be recalled for a job to proceed.
Conversion processing waits for the recall of the JCLLIB data sets to occur then proceeds with the conversion.
2. The JCLLIB data set is controlled (usually by an exclusive ENQ) by another job.
Conversion processing waits for the exclusive control to be released.

Even-Numbered Conversion Processing

Even-numbered conversion processing does not wait; it requeues jobs that need resources so that they are processed by the odd-number conversion processor. Jobs that have all their resources are converted immediately.

Note: To have at least one converter PCE free to process jobs at all times, you need to define a minimum of "2" converter PCEs in the PCEDEF initialization statement.

- If you need one job selected before another and you accept the "default" number of conversion processors or define more, you can control the sequence of job execution through the following types of procedures:
 - Delay the selection of the second job by coding TYPRUN on the JOB statement for that job
 - Specify a job class for the second job that will force the job into hold status
 - In a shared spool environment, assign a specific system affinity to each reader in your system through the RDR(nn) initialization statement, \$T RDRnn operator command, or on the /*JOBPARM statement for the job.
 - Add an additional step to the first job to submit the second job to the internal reader. As a result, the first job must complete before the second job can run.
 - You can affect the status of jobs entering the system, and the order in which JES2 selects jobs for processing by using the following JES2 installation exits:
 - Exit 2 for JOB statement scan
 - Exit 20 for end-of-job-input processing
 - Exit 6 for converter/interpreter text
 - Exit 14 for job queue work selection (before a job is selected)
 - Exit 49 for job queue work selection (after a job is selected by QGET)
 - Exit 22 for processing of TSO/E STATUS and CANCEL commands
 - Exit 44 for determining whether a job waits for migrated resources

z/OS JES2 Installation Exits gives details about using these exits.

JES2 Control of Batch Job Initiation

After conversion of a job's JCL, JES2 places the job into an appropriate class queue to await execution. If the job class is a JES2 managed class (JOBCLASS MODE=JES), then JES2 initiators select a job from the class queue (depending on

the job's priority) and pass control to MVS to execute your program. If the job class is a WLM managed class (JOBCLASS MODE=WLM), refer to "WLM Control of Batch Job Initiation" on page 97.

During execution, the initiator selects nonheld jobs in priority order within their class, and the nonheld classes in the order specified for that initiator. That is, the JES2 initiator selects the lowest priority job in the first nonempty class ahead of the highest priority job of the next class. Exceptions to these selection criteria are explained above and include:

- Held Jobs (TYPRUN=HOLD, JCLHOLD, or operator hold)
- Held Classes
- Held Execution Environment (\$P XEQ)
- Member Affinity (SYSAFF)
- Scheduling Environment
- Duplicate Job Name (optional in OS/390 Release 3)

Operator Control of the Batch Job Workload

The operator can ensure that the system resource manager has a sufficient number and variety of jobs to keep the system busy by varying the number of JES2 managed initiators and the classes from which they dequeue jobs. The mechanisms for such control are the JES2 commands to start, stop, set, and halt initiators (\$S lvvvv, \$P lvvvv, \$T lvvvv, and \$Z lvvvv). Each JES2 managed initiator controls the selection of one job at a time.

JES2 indirectly creates an address space for each active JES2 managed initiator. The operator can activate JES2 managed initiators and create additional batch job address spaces by means of the JES2 start initiator command (\$S lvvvv). In a similar manner, the operator can drain the JES2 managed initiators and cause termination of their address spaces by issuing the JES2 stop initiator command (\$P lvvvv).

The operator issues the halt initiator command (\$Z lvvvv) to deactivate a JES2 managed initiator, without terminating the address space (which is swapped out). This saves some time because JES2 need not recreate the address space if the operator starts the initiator later.

Table 15 summarizes the four useful commands for controlling batch workload (for syntax information, refer to *z/OS JES2 Commands*).

Table 15. JES2 Commands Useful in Controlling the Batch Job Workload

Desired Function	JES2 Command
Control the mix of batch jobs executable at the same time by assigning classes from which to select these jobs.	Set Initiator: \$T INITvvvv
Activate JES2 managed initiators and cause creation of additional batch job address spaces.	Start Initiator: \$S INITvvvv
Stop ("drain") JES2 managed initiators and end batch job address spaces.	Stop Initiator: \$P INITvvvv
Inactivate a JES2 managed initiator without terminating the address space	Halt Initiator: \$Z INITvvvv

Note: The initiator identifier vvvv represents a 1- to 4-digit ID.

Use the DUPL_JOB= parameter on the JOBDEF statement and/or the \$T JOBDEF,DUPL_JOB command to control whether JES2 is allowed to concurrently execute batch jobs of the same name in the same multi-access spool complex. Setting DUPL_JOB=DELAY instructs JES2 to wait for the first batch job to complete before starting the second with the same name.

Using Job Classes with JES2 Managed Initiators

Generally, you should assign the same job classes to jobs that have similar execution characteristics or jobs you are assigning special characteristics, such as:

- Rate of processor-to-I/O processing
- Use of special devices
- Number of devices used
- Use of central storage

For example, if several jobs are time-dependent and sort large amounts of data it might not be desirable to tie up all processor storage by having these jobs run concurrently. You could assign these jobs to class B (or C or D--class names have no inherent meaning); then if you define and start only one initiator to handle class B jobs, there will never be more than one of these jobs executing at once.

Assume you made the following assignments:

- Class B Jobs that are time-dependent
- Class C Jobs with high processor requirements
- Class D Jobs with high I/O requirements

You can specify initiator parameters such that:

- INIT(1) CLASS=BCD
- INIT(2) CLASS=CDB
- INIT(3) CLASS=DBC

If the three initiators (INIT(1), INIT(2), and INIT(3)) are processing jobs with the same priority and all necessary resources (for example, I/O devices and data sets) are available, then three jobs, one from each of the three different classes, run concurrently. If a job within one of the classes has higher priority than the others in the class, the system selects that job first.

JES2 Initiator Attributes

Use the INIT(nnn) initialization statement to identify each of the JES2 managed initiators you need on your system. On this statement, you specify:

- the number for the initiator
- the job classes that the initiator can select
- whether the initiator will start automatically when JES2 starts
- the name the operator uses to refer to the initiator (optional).

Naming Initiators: Installations can name ranges of initiators so that a single command controls all the initiators in that group. As an example, you can set up three initiators to process job classes A, B, and C:

```
INIT(101) CLASS=ABC,NAME=FRED
INIT(102) CLASS=CAB,NAME=FRED
INIT(103) CLASS=BCA,NAME=FRED
```

Now you can issue commands such as \$SI(FRED) or \$PI(FRED) to start or stop all initiators in that group.

JES2-managed initiators can include jobs that are in WLM mode, but these initiators will not select jobs from classes in WLM mode. All initiators (JES2 and WLM ones)

honor existing selection criteria. Those initiators in WLM mode only select jobs in a service class queue. The service class queue is passed to JES2 on "job select SSI." Exit 14 is not called for WLM initiators, but Exit 49 is invoked to allow installation modification of the job selection process.

Job Priority Aging

The system can increase the priority of a job based on the amount of time since the job entered the system if it is in a job class managed by JES2 initiators. You define this ability by specifying `PRTYHIGH=`, `PRTYLOW=`, and `PRTYRATE=` on the `JOBDEF` initialization statement.

`PRTYHIGH=` specifies the highest priority a job can achieve through automatic priority aging. `PRTYLOW=` specifies the lowest priority for a job to be eligible for automatic priority aging. `PRTYRATE=` specifies the number of times in a 24-hour period that the system will increase a job's priority (subject to the `PRTYHIGH=` limit) by one. `PRTYRATE=` has a default of 0, which means the system will not priority-age any jobs.

For example, if `PRTYRATE=48`, `PRTYLOW=4`, and `PRTYHIGH=10`, then all jobs with priorities of 4 to 9 will have their priority increased by 1 every 30 minutes (that is, 24 hours / `PRTYRATE` of 48 = 30 minutes) until the job priority reaches priority 10.

You set the lower priority limit, `PRTYLOW=`, to ensure that low priority work does not reach priority levels higher than new, more important work entering the system. In the previous example, all work with priorities 1, 2, and 3 will not priority age.

You set the upper priority limit, `PRTYHIGH=`, to ensure that high priority work maintains its importance, and doesn't compete with work that achieved its priority from length of time in the system. In the previous example, work with priority 11 through 15, will not priority-age but maintains higher priority than any jobs that can priority-age. See Figure 9 on page 97 for a graphic representation of the priority range setting.




Figure 9. Example of the Interaction of Priority-Aging Parameters, PRTYHIGH=, PRTYLOW=, and PRTYRATE= on JOBDEF Statement

Once the job is on the HARDCOPY queue, the only way to affect the priority is through the output priority.

For jobs that are run on a jobclass where MOD=WLM was specified on the JOBCCLASS(n) initialization statement, job priority aging has no affect.

WLM Control of Batch Job Initiation

Job initiators for WLM managed job classes are controlled dynamically by workload management. These initiators run under the Master Subsystem and are not assigned JES2 job numbers. WLM can adjust the number of initiators on each system based on:

- The queue of jobs awaiting execution in WLM managed classes.
- The performance goals and relative importance of this work.
- The success of meeting these goals.
- The capacity of each system to do more work.

The following must also be true for WLM managed initiators to be active:

1. WLM must be operating in goal mode. (All members of the MAS must be in goal mode for consistent operation.)

See *z/OS MVS Planning: Workload Management* for more details.

Controlling Batch Job Selection

Although workload management dynamically controls its initiators, there are several mechanisms by which you can manage them with JES2 commands:

- Limit the number of jobs in each class that can execute simultaneously in the MAS. See "Setting Job Class Limits for Execution" on page 91.

- Stop or start the selection of batch jobs by JES or WLM managed initiators on an individual system. See “Enabling Job Execution Selection” on page 91.
- Control the system or member affinity with the \$TJob command. See “Member Affinity” on page 90.

The scheduling environment for a job cannot be changed with operator commands. (See “Job Scheduling Environment” on page 90.)

- Immediately start the execution of a batch job in a WLM managed job class with the \$SJ operator command. Workload management will select the job for immediate execution from the list of systems where the job is eligible to run based on SYSAFF and SCHENV parameters. This is processed even if the job is held.
- Change the classification of jobs entering the system by altering characteristics of the job through the JES2 exits. See “Controlling Job Execution Through Exits” on page 91.

SMF Recording

To help you monitor and manage the batch job environment, SMF records include the following information:

SMF Type 26 Records: Workload Management section contains the service class name, scheduling environment, indicators that the job ran under a WLM or JES MODE initiator, or if the job ran because of \$SJ command.

SMF Type 30 Records: Additional fields have been added to the Performance Section including queue times and indicators that the job was modified through operator commands, forced into execution with the \$SJ command, or restarted.

SMF Type 72 Records: Subtypes 3 and 4 record the performance information for batch service classes including response times, velocity, transaction volumes, and JES delays.

See *z/OS MVS System Management Facilities (SMF)* for details.

Considerations for WLM Goals Applied to Batch Jobs

WLM goal types deserve special considerations for batch jobs. Remember that the queuing delays while waiting for initiation can affect response time calculations and performance indices. See *z/OS MVS Planning: Workload Management* for guidance on setting goals for batch jobs.

Batch jobs that are part of a critical path, such as the over-night “batch window” should remain in JES managed job classes.

Alignment of Initiator Mode and Service Classes: All jobs with the same service class should be managed by the same type of initiation. For example, if job classes A and B are both assigned to the HOTBATCH service class, and JOBCLASS(A) is MODE=WLM, while JOBCLASS(B) is MODE=JES, workload management will have a very difficult time managing the goals of the HOTBATCH service class without managing class B jobs.

Queue Delay Measurements: If you have large job execution queues, the queue delay can dominate the response time or velocity. This may cause the system to not address other delays because it would not significantly affect the performance index (PI).

Response time does not include TYPRUN=HOLD or JCLHOLD delays, but does include the following:

- Operational delays (jobs or job class held by operator command)
- System or resource affinity delay
- Scheduling delay due to class limits, duplicate jobnames
- Time waiting for an Initiator

Multiple JES2 MAS Complexes in a Sysplex: There is no requirement that all systems in the sysplex be in the same MAS complex. However, the WLM policy is sysplex-wide and independent of the JES2 member or MAS complex.

- Jobs with the same classification attributes (job class, etc.) will be assigned the same service class, no matter which MAS they are in unless the subsystem collection name is included in the classification attributes.
- The service class determines the goal regardless of which MAS they are in.
- All jobs in the sysplex with the same service class should be managed by the same type of initiation. If you split a service class between WLM and JES managed initiators, workload management will have a very difficult time managing the goals. [JOBCLASS(c) MODE= setting should be the same in all MASes in the sysplex.]
- Limiting the number of jobs in execution by class through the JOBCLASS(c) XEQCOUNT parameter is only MAS-wide, not sysplex wide.

WLM Poly-JES Considerations: If two copies of JES2 in the same MVS system (poly-JES) are not sharing the same spool, workload management initiators can select jobs from both the primary and secondary JES.

WLM does not support a secondary JES2 subsystem in the same MAS as the primary. Workload management initiators will only select jobs from the primary JES if the secondary JES is sharing spool with the primary.

The Initiator Cataloged Procedure

SYS1.PROCLIB must contain an initiator cataloged procedure (named INIT) to create job address spaces for both JES2 and WLM managed initiators. JES2 and WLM use the MVS START command to create a system initiator. You can control the number of JES2 initiators by starting and stopping initiators. You cannot control the WLM initiators directly with operator commands.

Figure 10 illustrates the initiator cataloged procedure as supplied by IBM:

```
//IEFPROC EXEC PGM=IEFIIC,DPRTY=12
```

Figure 10. IBM-Supplied INIT Procedure

System Resource Manager Control of the Batch Job Workload

With JES2 managed initiators, you can have more batch jobs initiated and more time-sharing users logged on than the number of address spaces in central storage can accommodate. The System Resources Manager (SRM) can remedy this problem by swapping out heavy resource-using job(s).

Although you might expect over-initiation could compete with and slow the progress of the more important jobs, the SRM addresses this problem. The SRM processes individual jobs according to their service class goals and relative importance.

When the load on the resource eases, the SRM can choose from a varied mixture of swapped-out jobs to even the job mix.

Job Monitoring

You can monitor a job through:

- Elapsed time (time since the job started)
- Execution time (actual time spent executing instructions)
- Output
 - Lines and cards produced
 - Pages produced
 - Number of bytes of output produced.

Use the ESTIME statement to cause JES2 to write a message to the operator when a job exceeds the elapsed time specified by the JOBPARM statement, and an additional message at each interval specified by the INT= parameter on this same statement. You can use the IEFUTL installation exit routine to enforce these values, if the IEFUJV installation exit routine places the time in the SMF user ID field. See *z/OS MVS Installation Exits* for information about these exits.

The JCL EXEC statement, the JOB statement, and the converter parameters on the JOBCLASS(v) statement allow you to specify the maximum execution time for a job. If a job exceeds this value, the system enters an IEFUTL installation exit routine, which can cancel the job or allow it to continue (after writing a warning to the job submitter). See *z/OS MVS Installation Exits* for information about this exit.

Use the ESTLNCT, ESTPAGE, ESTPUN, and ESTBYTE JES2 initialization statements to specify the total number of printed lines, printed pages, punched cards, and SYSOUT bytes that a job can produce before JES2 takes action. The OPT= parameter specifies the action JES2 should take. You can allow the job to continue after writing a message to the operator or cancel the job with or without a dump.

Even if a previous step ends with a completion code of 722 (output limit exceeded), the MVS scheduler selects (and begins executing) the next step if COND=EVEN or COND=ONLY appears on the EXEC statement. This step does not end immediately with ABEND722 for producing excessive line, page, or byte SYSOUT but ends when the job exceeds the next excess output interval (that is, NUM= specification plus INT= specification for the specific ESTLNCT, ESTPAGE, or ESTBYTE initialization statement).

Use JES2 Exit 9 to control job output overflow. See *z/OS JES2 Installation Exits* for information about this exit.

Your installation can specify SMF output limiting by class, with the JOBCLASS JES2 initialization statements. SMF can monitor the output (OUTLIM= on DD statement) for each data set.

Monitoring the Successful Completion of a Job

JES2 displays the successful or unsuccessful completion of a batch job with the \$HASP165 message. This message is displayed to an interactive user if the NOTIFY parameter is specified on the JCL JOB statement, or the JECL /*NOTIFY statement is specified. You can see the completion code or ABEND code as follows:

- Jobs ending normally have the maximum condition code displayed
\$HASP165 job_name ENDED AT node_name MAXCC=nnn
- Jobs ending abnormally have the ABEND codes displayed:
\$HASP165 job_name ENDED AT node_name ABENDED Sxxx Unnnn

Also, you can display the ABEND or MAXCC for a job still on the JES2 queues before they are purged, with the \$DJ(),CC command.

Entering Commands from a Job Stream

Depending on your security policy, JES2 accepts JES2 commands and MVS commands at different points in a job stream, with different types of control. A job stream is the set of jobs submitted between the physical start of a reader and physical end-of-file, or between the opening and closing of an internal reader data set. Refer to Figure 11 on page 101 for a pictorial representation of the following description.

JES2 accepts JES2 commands in your jobstream in the form /*\$command (for example, /*\$S) in front of the JOB JCL statement. JES2 also accepts MVS commands in the /*\$VS, 'systemcommand' statement if the command authority is similar to the authority for accepted JES2 commands. An example of submitting an MVS command this way is /*\$VS, 'V OCE,offline'.

JES2 ignores JES2 commands found in the job stream between the first JOB statement and EOF. Also, JES2 ignores JES2 commands entered in a job stream through the network job receiver.

The converter executes any MVS commands (//name COMMAND 'command' where the name parameter is optional) that appear in the job stream after the first JOB statement. Whether the converter actually issues the command depends on what you specified for the converter parameters. JES2 ignores all MVS commands appearing before the first JOB statement.




Figure 11. Entering Commands from a Job Stream

Execution Batch Monitoring (XBM) Facility

The execution batch monitoring facility allows a user with minimal knowledge of JCL to process data. The user need only provide a valid MVS JOB statement and input data. This facility is useful for:

- Compile-and-go debugging compilers
- File-inquiry programs
- Hardware or software system emulators

XBM treats all statements including the JOB statement (up to the next JOB statement or end-of-file) except for /*ROUTE and /*XMIT statements as input to a processing program. To use this facility:

- The XBM= parameter on a JOBCLASS initialization statement must name a cataloged procedure that resides in a procedure library named in the JES2 start procedure.
- The user must specify that job class on the JOB statement that is submitted.
- The EXEC statement of the cataloged procedure associated with the specified job class must name the program that processes the user's input data.

When a user submits a JOB statement specifying a job class that is associated with a cataloged procedure, JES2 generates an EXEC statement naming that procedure, and a SYSIN DD * statement. JES2 then makes a copy of the original JOB statement and places it after the generated statements. This JOB statement, and any other JCL statements that the user might have coded, except /*ROUTE and /*XMIT JES2 control statements, as well as the input data the user has provided, becomes input to the program named in the procedure. When you code the program to be invoked by the procedure, be sure to handle any JCL statements the program might encounter in the input stream (unless you restrict your users to only the JOB statement). Also, your program must define the DDNAME SYSIN as input.

Installations currently using the XBM facility prior to JES2 Version 3.1.3 can convert their existing applications with minimal impact to their customers. You must:

1. Ensure all of your customers have valid MVS JOB cards in their job streams.
2. Remove the XBATC parameter from the JOBCLASS(v) and JOBDEF initialization statements.
3. Specify the name of the procedure you were using to process input for each individual job class on the XBM= parameter of the JOBCLASS(v) initialization statement. JES2 no longer generates the name of the procedure it is invoking so you need only provide one procedure name for each initiator class.
4. If your existing processing program reads past end-of-file in an attempt to obtain more data, JES2 issues a bad return code. This version of XBM processes each job individually, and does not support the additional read. You must change your processing program to accept the end-of-file as a valid end-of-input.
5. If you require the ability to accumulate statistics for a specific class of work, or data related to the number of jobs processed, you **must rewrite** your processing program to maintain that information between jobs because your program will end between jobs.
6. Ensure all user JCL contains valid JOB statements. Execution batch monitoring jobs must pass all converter validation before execution.

Note that the majority of the previous benefits of using the execution batch scheduling facility no longer exist. You might want to convert jobs that currently use the facility to jobs with the appropriate execution JCL as soon as convenient. Also, all previous restrictions on dynamic allocation no longer exist.

Using the Execution Batch Monitoring Facility

Before using the execution batch monitoring facility you must:

- Write and test the program that will process the input. This program must handle any JCL it encounters in the input stream and use DDNAME SYSIN as input.
- Write and test a procedure to invoke your program.
- Place the procedure in a library defined in the JES2 start procedure. Figure 12 on page 103 shows the contents of an example procedure named ORDPROC.

```
//PROCESS EXEC PGM=ORDERIT
//INPUT DD DDNAME=SYSIN
//OUTPUT DD DSN=NEEDED.BOOKS,DISP=OLD
//CONTROL DD DSN=BACKORD.INVENTOR,DISP=SHR
```

Figure 12. Contents of the Example *ORDPROC* Member

- Use **XBM=** on the **JOBCLASS(v)** initialization statement to specify the name of the data set member that contains the procedure. Figure 13 on page 103 shows a **JOBCLASS(v)** statement coded to take advantage of the execution batch monitoring facility.

```
JOBCLASS(R) ACCT=YES,COMMAND=IGNORE,LOG=NO,MSGLEVEL=(2,0),
PERFORM=123,PGMRNAME=YES,PROCLIB=02,
XBM=ORDPROC
```

Figure 13. Specifying the Procedure on the *JOBCLASS(v)* Statement.

- Issue **\$P JES2** to stop JES2 and close the procedure libraries.
- Issue **S JES2** to restart JES2 and open the procedure libraries. JES2 can now access your procedure and you can submit jobs that use the procedure.

Figure 14 is an example of the JCL coded to submit input to the *ORDERIT* program. The **/*ROUTE** statement in the example routes the output to the destination, **STR15**.

```
//ORDER12 JOB (STR12,15,5845),HUTCH,CLASS=R
/*ROUTE PRINT STR15
JES2 Exits J. Vazquez
JES2 Commands P. Kaskovich
JES2 General Information D. Wagenaar
JES2 Introduction D. Pizzuto
JES2 Init Tuning Reference T. Koman
JES2 Init Tuning Guide J. Hutchinson
```

Figure 14. Example JCL to Invoke *ORDERIT*

If the procedure fails, you can temporarily use another procedure to process the input by:

1. Holding the job classes that use the failing procedure.
2. Issuing **\$T JOBCLASS(v),XBM=newproc** to point the job class to a different procedure.
3. Releasing the job classes you held in the first step.

You can enable the execution batch monitoring facility for a previously defined job class, or switch procedures associated with a job class with the **\$T JOBCLASS(v)** command. The job class can be managed by JES2 or WLM initiators.

Output

JES2 provides the following facilities for controlling system output by:

- Queuing of each output unit of work for a job according to a priority based on the volume of output represented by that work unit or the priority specified on the JCL OUTPUT statement.
- Minimizing operator interaction due to forms, carriage tape, and print train loading for impact printers, and forms, overlay frames, and burster loading for non-impact printers.
- Supporting devices other than printers and punches by routing SYSOUT data to specific external writers through an external writer interface.
- Priority aging of job output elements based on priority parameter specifications, such that the longer the output remains on the output processing queues, the greater its priority becomes.
- Supporting a functional subsystem for non-impact printers (such as the 3800-3 functional subsystem printer) through a functional subsystem interface.
- Routing SYSOUT data sets among nodes in the network.
- Specifying the number of records processed, per job, on printers or punches.
- Holding the writing of an output data set and gathering data sets with the same set-up characteristics for printing as a single unit of output work.
- Supporting the purging of output from jobs, SYSOUT, started tasks (STCs), and time sharing users (TSUs) if the job ended normally (that is, as expected).
- Ensuring users can use specific output devices and output devices have a sufficient security to process specific output. See “Part 7. Providing Security for JES2” on page 341 for information on output security.

The system programmer controls system output by:

- Specifying print train and either carriage tape name or forms control buffers for SYSOUT directed to printers with these features, plus supporting the 3525 print and interpret features for SYSOUT data sets.
- Specifying all options and features of the 3800 printer for SYSOUT data sets directed to the 3800.

Default Data Set Characteristics

JES2 assumes defaults for any data set characteristics not specified on the SYSOUT DD statement, the JCL OUTPUT statement or the JES2 /*OUTPUT control statement. If a job does not specify an FCB, UCS, or FLASH parameter, JES2 uses the FCB, UCS, or FLASH default value specified by your installation. JES2 uses the name '****' when requesting a default FCB or UCS image from the operator. The operator satisfies this request by mounting any image specified as a default. If the job does not specify one or more of the parameters (FCB, UCS, or FLASH), then any default will satisfy it.

Identify the form used for all data sets not specifying a form during JES2 initialization in the STDFORM parameter on the OUTDEF statement. This is the standard form for both printers and punches.

Output Priority

JES2 queues a job for output processing when the job completes execution. You can change the default priority assigned to the output by coding the PRTY= keyword on the JCL OUTPUT statement. PRTY= assigns a single priority level between 0 and 255 to all work units within a particular output group. The keyword takes effect if you also specified PRTYOUT=YES on the OUTDEF initialization statement; PRTYOUT=NO is the default.

JES2 creates output groups during output processing or during execution in the case of spin (FREE=CLOSE or SPIN=UNALLOC on the DD statement) data sets. Each output group represents a unit of output work to JES2. JES2 places the output group in the job output element queue in order of output priority. If you did not specify a priority on the JCL OUTPUT statement, JES2 computes a priority for each output group from the tables specified by the PRIORITY= parameter on the OUTPRTY initialization statement.

Also, JES2 uses the RECORD= parameter (for line data), the PAGE=parameter (for page data) or both the RECORD= and PAGE= (for data containing line and page data) with the PRIORITY= parameter to determine the priority of the output. JES2 bases the priority on the total number of print lines, punch cards, or pages in the data set which the output group represents. If the output group represents a data set containing both line and page data, the output priority is the average of the priorities specified by the RECORD= and PAGE= parameters, respectively. The following table shows the default values for the priority calculation.

Table 16. Priority Calculation Default Values

For RECORD:	RECORD	n
RECORD values are estimates of the job output lines and cards	2000	1
	5000	2
	15000	3
	279620	4
	.	.
	.	.
	.	.
	16777215	9
For PAGE:	PAGE	n
PAGE values are estimates of the number of job output pages	50	1
	100	2
	300	3
	16777215	4
	.	.
	.	.
	.	.
	16777215	9
For PRIORITY:	n	PRIORITY
The n value is determined from the PRIORITY table.	1	9
The PRIORITY table shown contains the default for the corresponding n values	2	8
	3	7
	.	.
	.	.
	.	.
	9	1

If the total number of output records (lines or cards) is 2000, then:

From RECORD, 2000 output records indicates n = 1
From PRIORITY, n = 1 indicates PRIORITY = 9

If the total number of output pages is 300, then:

From PAGE, 300 output records indicates $n = 3$
From PRIORITY, $n = 3$ indicates PRIORITY = 7

If the total number of output is 2000 lines **and** 300 pages, then the output priority is the average of both types of output based on the RECORD and PAGE values as follows:

From RECORD, 2000 output records indicates $n = 1$
From PAGE, 300 output records indicates $n = 3$
The average value of $n = (1 + 3) / 2 = 2$
From PRIORITY, $n = 2$ indicates PRIORITY = 8

By specifying other values for the tables (during JES2 initialization), you can more closely control your installation's priority assignments. If you do build your own priority table based on estimated record/page counts, be certain that you supply the values in ascending order as the RECORD, PAGE, and PRIORITY(n) values are in the default tables, above. This requirement exists because JES2 uses the RECORD= or PAGE= values in a "less than or equal to" order when calculating a priority that does not exactly match the values in the tables.

JES2 selects output groups for output processing based on the job's output priority. You can cause the priority to increase through the priority aging feature. You can set the original priority on the OUTPRTY(n) statement. However, if the priority is within the limits set by PRTYLOW= (the minimum) and PRTYHIGH= (the maximum), JES2 increases the priority of the job at a rate specified by PRYORATE=. See "Output Priority Aging" for additional information about output priority aging.

When a job completes output processing (all of its output groups created and added to the job output element queue), JES2 queues the job for hard-copy.

When assigning such things as priority classes and forms requirements for data sets, you should balance the choices against the criteria JES2 uses to select the output data sets to process.

Output Priority Aging

JES2 can increase the priority of a job's output based on the time since the output was created. You define this ability by specifying PRTYHIGH=, PRTYLOW=, and PRYORATE= parameters on the OUTDEF initialization statement.

PRTYHIGH= specifies the highest priority which output can achieve through automatic priority aging. PRTYLOW= specifies the lowest priority for a job to be eligible for automatic priority aging. PRYORATE= specifies the number of times in a 24-hour period that the system will increase a job's priority (subject to the PRTYHIGH= limit) by one. PRYORATE= has a default of 0, which means the system will not priority age any output.

For example, if PRTYRATE=48, PRTYLOW=100, and PRTYHIGH=200, then all jobs with priorities of 100 to 199 will have their priority increased by 1 every 30 minutes (that is, 24 hours / PRTYRATE of 48 = 30 minutes) until the job priority reaches priority 200.

You set the lower priority limit, PRTYLOW=, to ensure that low priority output does not reach priority levels higher than new, more important output entering the system. In the previous example, all output with priorities between 1 and 99 (inclusive) will not priority age.

You set the upper priority limit, `PRTYHIGH=`, to ensure that high priority output maintains its importance, and doesn't compete with output that achieved its priority from length of time in the system. In the previous example, output with priority 200 or higher, will not priority age but maintains higher priority than any output that can priority age. See Figure 15 for a graphic representation of the priority range setting for output.




Figure 15. Example of the Interaction of Priority-Aging Parameters `PRTYHIGH`, `PRTYLOW`, and `PRTYRATE` on `OUTDEF` Statement

Output Processing

The JES2 print/punch processor, the external writer, the network `SYSOUT` transmitter and spool offload `SYSOUT` transmitter can select only data sets which already have output groups constructed. Varying the number of output groups, (`JOENUM` parameter on the `OUTDEF` initialization statement) influences the processing of output.

Specifying many output groups makes more work available for selection within the configuration; however, the increased number of output groups also increases the size of the checkpoint data set thus adversely affecting performance.

An output group that does not yet describe a unit of work is a “free” JOE. When the building of output groups for a job depletes the number of available free JOEs, the job or spin data waits until more output groups become available.

The JES2 output processor builds output groups for a job without making a distinction as to whether the routing of the data sets is for the local node or for some other node. JES2 makes the distinction when it adds the output groups to the output queues; JES2 then places all the output groups for the local node on one of the class queues, and places all the others on the network queue.

Output Data Set Groups

An output group can point to a data set group that defines data sets that have identical characteristics and contain the output of a job, a started task, or a time-sharing user. Each data set group is a processing entity with a set of processing characteristics.

JES2 groups output for jobs processed at the local node use the following processing characteristics:

- Burst specification (BURST)
- Output class (CLASS)
- Destination (DEST)
- Forms control buffer name (FCB)
- Forms overlay frame (FLASH)
- Forms (FORM)
- Group name (GROUPID)
- Output disposition (OUTDISP)
- Process mode (PRMODE)
- Print train (UCS)
- Installation writer name (WRITER)

You can use the OUTPUT JCL statement to describe these characteristics. Note that the SYSOUT DD statement and the /* OUTPUT JECL statement support all these characteristics except GROUPID and OUTDISP.

JES2 also groups output data sets on the following criteria which a user can specify on the OUTPUT JCL statement:

- Address
- Building
- Department (DEPT)
- Name
- Print complete notification message (NOTIFY)
- Room
- Title

These fields can also be modified through SDSF while output resides on the output or hold queue.

When JES2 groups on the information on these fields, it attempts to match the character string exactly. Therefore, it is important to ensure the user specifies the **exact** string in each of the above so JES2 can group the output properly. For example, JES2 will not group NAME='JOHN' and NAME='JOHN ' together.

You can change the SYSOUT characteristics that affect grouping by using JES2 Exit 40. See *z/OS JES2 Installation Exits* for more information about Exit 40.

Table 17 on page 109 illustrates how one output group can represent one of several SYSOUT data sets.

Table 17. Relationship of SYSOUT Specification to Number of Job Output Elements

SEVEN OUTPUT GROUPS BUILT		
1	-	SYSOUT=(A,,4PLY), UCS=PN
2	-	SYSOUT=C,UCS=PN
3	-	SYSOUT=A
4	-	SYSOUT=B
5	-	SYSOUT=A,FLASH=FL01
5	-	SYSOUT=A,FLASH=FL01,MODIFY=CM03
6	-	SYSOUT=C,FCB=STD3,UCS=GF10
6	-	SYSOUT=C,CHARS=(GF10,FM10),FCB=STD3
7	-	SYSOUT=C,CHARS=(GF10,FM10),FCB=STD3,UCS=PN
3	-	SYSOUT=A
THREE OUTPUT GROUPS BUILT		
1	-	SYSOUT=A
1	-	SYSOUT=A
...
2	-	SYSOUT=B
1	-	SYSOUT=A
2	-	SYSOUT=B
:		
:		
3	-	SYSOUT=(A,,2PLY),FCB=8LPI
:		
:		
1	-	SYSOUT=A

JES2 duplicates output groups built for job-related output depending on the number of job copies requested on the /*JOBPARM statement (up to the maximum allowed by the COPIES= parameter on the OUTDEF statement). This allows the devices available for output to govern the number of copies processed for a particular job. JES2 uses several factors to group SYSOUT data sets. The groups also conform to a set of rules, discussed below. Table 18 on page 110 summarizes these rules.

JES2 uses the following factors to group output:

- The data set output class matching the job's message class
- The USERSET specification on the OUTDEF statement.
- The user assigned an output group name using the GROUPID= keyword on the JCL output statement.
- The DMNDSET parameter specification on the OUTDEF statement.

JES2 forms output groups whose data sets always agree on the following characteristics:

- address
- building
- department
- destination
- external writer
- name
- output class
- output disposition
- output group name
- print complete notification message
- process mode

- room
- title

If DMNDSET=YES on the OUTDEF initialization statement and the data set matches the job's message class or if USERSET=YES on the OUTDEF initialization statement and the user assigned the output group a name, then JES2 scans the setup characteristics of the output group's data sets to determine which, if any, of the setup characteristics vary. Otherwise, the output groups will also agree on setup characteristics.

Table 18. Interrelationship Between the Four Factors Affecting Output Grouping

DMNDSET= *	DOES MSGCLASS AND OUTPUT CLASS MATCH?	USERSET=YES		USERSET=NO	
		OUTPUT GROUP NAME ASSIGNED		OUTPUT GROUP NAME ASSIGNED	
		YES	NO	YES	NO
YES	YES	1	1	1	1
	NO	1	2	2	2
NO	YES	1	2	2	2
	NO	1	2	2	2

Notes:

1. * USERSET and DMNDSET are parameters on the OUTDEF initialization statement.
2. Data sets within groups formed agree on class, external writer, destination, process mode, output disposition, and output group name. However, setup characteristics (those characteristics that determine the data set groups eligible for processing a given device) can vary.
3. Data sets within groups formed agree on class, external writer, destination, process mode, output disposition, output group name and setup characteristics.

To delay printing data sets, an installation can specify:

- Reserved classes
- HOLD=YES on a JCL DD statement
- OUTDISP=HOLD on the JCL Output statement
- OUTDisp=HOLD or LEAVE on one of the following initialization statements:
 - JOBCCLASS
 - OFF(n).SR
 - OFF(n).ST
 - OUTCLASS

“Output Disposition for SYSOUT Data Sets” on page 124 discusses the OUTDISP parameter. *z/OS MVS JCL Reference* explains HOLD=YES on a JCL DD statement. Note that the use of the GROUPID= keyword on the JCL OUTPUT statement influences data set gathering. If your installation allows user control of output groups by specifying USERSET=YES on the OUTDEF statement, you can form output groups with dissimilar output characteristics.

JES2 does not group spin data sets; each data set constitutes a “group” of one data set.

SMF Record Summary: Job-Output Related Information

The following lists the SMF records that contain job-output related information. For a complete list of the record contents, see *z/OS MVS System Management Facilities (SMF)*.

Table 19. SMF Records Containing Job Output Information

Record Number	Action that Causes the Record to be Written
6	When JES2 finishes processing a job output element it will write this record if TYPE6=YES in the JOBCLASS statement.
26	After processing all SYSOUT data sets for a job, JES2 writes this record if TYPE26=YES in the JOBCLASS statement. Exit IEFUJP can also override the writing of this record.
57	After transmitting an output group to another NJE node, JES2 writes this record.

JES2 Exit 21 or SMF Exit IEFU83 can be used to override the writing of these records.

Routing Output to Other Nodes

Output groups on the network queues are grouped by data set forms requirements, SYSOUT class, and other selection criteria. If you decide to route output on the network queue to the local node, remember that routing output does involve calls to an installation's security product, which can impact command performance. JES2 removes the output group from the network queue and places it on the appropriate local class queue. Similarly, JES2 routes output groups originally destined for local output to another node by removing them from their class queue, changing their route codes, and placing them on the network queue.

The JES2 commands that deal with output routing (for example, \$R and \$O) allow routing and rerouting of data sets. JES2 places the current routing of a data set in the data set header whenever the data set is transmitted.

The network SYSOUT transmitter selects output groups from the network transmission queue, which is ordered FIFO (first-in-first-out) within priority. For data sets created on the local node, the network SYSOUT transmitter creates network data set headers. The network SYSOUT transmitter transmits the data set headers, along with a job header, job trailer, and data set records over an NJE line to the destination node specified in the routing information for the data set. This transmission can be either store-and-forward through intermediate nodes, or direct transmissions to the destination node.

JES2 attempts to transmit as one job, any non-spin SYSOUT which are created under a single job and directed to a common destination (or along a common path). This processing is performed even if multiple SYSOUT data sets are grouped into different output groups with different output priorities.

At the other node, a network SYSOUT receiver receives the NJE headers and data sets. The network SYSOUT receiver uses the information in the NJE job header to create a new job on the receiving system. As a result of this processing, the network SYSOUT receiver places a job on the output queue. The output processor on the receiving node treats this job as a locally completed job. The output processor creates output groups describing the data set, thus making it ready for local print/punch processing or further network transmission, depending on the routing specified for the data sets.

NJE Transmission Selection: You can specify multiple transmitters (and receivers) for a line as described in “Specifying Transmitters and Receivers” on page 276. For individual SYSOUT transmitters, you can also specify work selection characteristics based on the size of SYSOUT files as described in “Specifying Work Selection Values for NJE Transmitters” on page 277.

NJE file sizes can range from very small (for example, one record, such as a Netmail acknowledgement) to very large (millions of records). After a transmitter has selected a file, it does not interleave it with other files or voluntarily interrupt the transmission until that file is completely transmitted. If the line drops or the transmission is otherwise interrupted, the entire file must be re-transmitted from the beginning.

You can use the work selection (WS=LIM) parameter on the L(nnnn).ST(n) statement to cause a SYSOUT transmitter to select files based on their size, so as not to tie up a transmitter a long time with very large files. This allows a transmitter to be available for timely delivery of small files. See “Specifying Work Selection Values for NJE Transmitters” on page 277 for more information.

Considerations for Output Produced by APPC Transaction Programs

Advanced Program-to-Program Communication (APPC) is an implementation of the Systems Network Architecture (SNA) LU 6.2 protocol that permits interconnected systems to communicate and share the processing of programs. Installations can use APPC to allow MVS systems to participate in a cooperative processing environment.

Application programs that use APPC communication calls to perform cross-system requests are called **transaction programs**. Transaction programs can communicate with other transaction programs that reside on local or remote systems. For example, an installation might choose to create a transaction program on an IBM Personal System/2 (PS/2)* workstation and use APPC to access MVS services on a host, such as updating a large data base; the MVS transaction program could subsequently return messages or data to the workstation. Such applications allow installations to take advantage of the inherent usability of the PS/2 and the power and resources of an MVS host computer.

APPC transaction programs can exploit certain JES2 facilities, such as printing, network job entry (NJE), and job submission. JES2 treats all SYSOUT produced by APPC transaction programs as spin data sets. APPC transaction programs do not run as JES2 jobs; instead, transaction programs are associated with APPC transaction initiators, which are long-running jobs that can sponsor many transaction programs.

Output from APPC will have the 'PROTECTED' indicator, but this has nothing to do with RACF or other security servers. Also, the 'PROTECTED' indicator is not exclusive to APPC; it is found in OMVS and in other transactional environments where the transaction output is associated with the initiators such as ASCHINIT and BPXAS.

Because APPC work is treated differently from other JES2 work, you should be aware of the following processing considerations for SYSOUT data sets created by a transaction program:

System Data Sets

Because an APPC initiator can represent many transaction programs, the following system data sets are treated differently for APPC work than for other types of work in the system:

Data Set

APPC Considerations

\$JOURNAL

Job journal data sets are not produced for APPC transaction programs. Therefore, transaction programs cannot be automatically restarted.

JESMSGLG

JES2 does not support JESMSGLG data set processing for APPC transaction provided programs. However, JES2 does write messages concerning APPC transaction programs into the TP message log which can be used for recovery and problem determination when an error occurs while an APPC transaction program is processing. See *z/OS MVS Planning: APPC/MVS Management* for additional information about the TP message log.

JESYSMSG

JESYSMSG data sets are not produced for APPC transaction programs.

JESJCL

Support for JESJCL is equivalent to that provided for other started tasks.

See *z/OS MVS Planning: APPC/MVS Management* for additional information about understanding and implementing APPC in an MVS environment.

Output Class Assignment

A problem program assigns its output an output class which JES2 processes. You can name one of a maximum of 36 SYSOUT classes by specifying the SYSOUT= keyword on the DD statement or by using the CLASS= keyword on the JCL OUTPUT statement. You can specify any single letter (A-Z), number (0-9), or asterisk as a class. An asterisk indicates the class assigned is the same as that assigned to the message class as specified by MSGCLASS= on the JCL JOB statement. The names have no inherent meaning; they simply group similar output characteristics. The designation of a class as containing print or punch data, during JES2 initialization, is only for output limiting and job accounting purposes and has no bearing on the class assigned to the actual device.

JES2 assigns output class characteristics (such as data set and message hold status, track celling, and print-punch specification) on the OUTCLASS(v) initialization statement. Refer to the OUTCLASS(v) statement in *z/OS JES2 Initialization and Tuning Reference* for a complete description of this statement.

Characteristics of Output Classes

Assign JES2 print/punch processors and external writers only to specific classes of output. Make the assignment:

- During JES2 initialization for JES2 devices.
- In the external writer cataloged procedure for external writers.
- At any time, for JES2 devices, by using JES2 modify (\$T) commands.
- For external writers, by specifying classes on the MVS START or MVS MODIFY commands. See *z/OS MVS System Commands* for more information on these MVS commands.

If no device is active for an output class, output for that class remains on the queue until you start a device for that class.

Assign output classes in a manner that distinguishes types of output and results in the most efficient use of devices. However, keep the following in mind when assigning classes:

- Distinguish between data processed by standard JES2 writers and data processed by external writers.
- Allocate separate classes for data destined for different devices and data destined for similar devices but with different characteristics. It is not necessary, however, to use classes to separate data with different UCS and FCB requirements if a JES2 writer is to process the data because JES2 handles these parameters automatically. Use separate classes if an external writer will print this data.
- Assign classes to give different priority to different types of data, such as output printed on a different work shift.
- Do not use different classes to give priority to short data sets as the JES2 priority calculation is adequate for this purpose.
- Coordinate output classes in an NJE environment so print and punch classes are consistent among nodes in the network. The destination node places SYSOUT data sets in the class queues indicated in the NJE header. The class at the destination node determines the processing used for the data set.

If the classes are not consistent, the receiver might not get data in the expected form. For example if class G is print output on node A and punch output on node B, routing class G data from node A to node B causes print output to be punched.

By specifying a process mode (PRMODE) for the particular device on which you require the system to process the SYSOUT data set(s), you avoid the problem of multiple destinations assigning the same output class to different devices. For example, if you send a SYSOUT data set to another node (for printing on a 3800 printer), specify PRMODE=U3800 on the PRT(nnnn) initialization statement for that device. If you then specify PRMODE=U3800 on the JCL output statement of the desired data set, JES2 allows the device with PRMODE=U3800 to select that data set for printing. Additionally, JES2 can select any other work which matches any other process modes specified for that device.

Blank Truncation

Use the BLNKTRNC parameter on the OUTCLASS(v) statement to turn off blank truncation for any non-page-mode data (the default is BLNKTRNC=YES). This parameter specification has no effect on page-mode data, but generally saves significant spool space for line-mode data. In a typical page-mode SYSOUT data set that contains a mixture of page- and line-mode data, any spool savings applies only to the line-mode records. Do not set BLNKTRNC=NO except for those data sets that require right-hand padding with blanks to produce correct alignment. If required, set aside one or more specific classes for no blank truncation.

If you send SYSOUT data sets that have not been blank-truncated to a node initialized with blank truncation set on for that particular output class, the receiving node will truncate the data set. This same 'truncation rule' holds true for individual members of a multi-access spool complex. If a member initialized (or defaulted) with BLNKTRNC=YES executes a job it receives from a system where BLNKTRNC=NO, the data set is blank truncated regardless of the truncation characteristic of the sending member's SYSOUT class.

Setup Characteristics

As established during JES2 initialization (and perhaps altered by the operator), each JES2-controlled printer and punch possesses setup characteristics. Setup

characteristics for impact printers (for example, the 1403 and 3211) and punches are: process mode, forms, print train, and either carriage control tape or FCB. (For a 1403 printer, JES2 uses the FCB parameter as the carriage control tape name. JES2 requests that the operator mount carriage tapes by this name in a manner similar to mounting forms.) For non-impact printers (for example, the 3800 and 3820 printers), setup characteristics are: process mode, forms, flash, burst, UCS, and FCB specifications.

Setup characteristics determine the data set groups eligible for processing on a given device. Each locally attached printer and punch has either a route code of LOCAL or a specific device-name route code. If the device has a specific route code name or names, it is eligible to process only those data sets that JCL or the operator specifically routes to it. The route code name assigned to a remotely attached printer or punch is either the installation-assigned name of a remote pool of devices or the name of the workstation the device attaches to.

Demand Setup and Output Data Set Grouping

This facility allows users to define the grouping of output data sets. For example, a user can group all of a job's output together, including the JES2 system data sets and assign a single output class to the group. Such grouping directs JES2 to print all the data sets in the group on continuous paper. When grouping data sets, the data sets must have the same **grouping characteristics**; these include output class, destination, external writer name, security label, and process mode. Refer to *z/OS MVS JCL User's Guide* for a description of how a user can control grouping characteristics through use of the JCL OUTPUT statement.

Demand setup is the setup of an output devices based upon user needs. **Demand setup groups** are groups of data sets with the same user-defined setup characteristics. The DMNDSET= and USERSET= parameters on the OUTDEF statement allows users to define demand setup groups. DMNDSET= allows users to define a single group to data sets with different device setup characteristics. USERSET= allows users to create JCL-defined output groups.

Spin Data Set Processing

Coding FREE=CLOSE or SPIN=UNALLOC in the JCL of a SYSOUT DD statement or specifying the DALCLOSE text unit key on a dynamic allocation (SVC99) parameterlist for a SYSOUT data set causes JES2 to spin the data set for output processing when it is closed. JES2 then has the capability of performing output processing on the data set while the job continues execution.

In most cases, JES2 frees spool tracks allocated to the data set after printing, cancelling, or transmitting the last copy of the data set.

For applications that dynamically allocate a spin SYSOUT data set (unallocation at Close - Key X'001C') but fail to issue FREE=CLOSE or SPIN=UNALLOC, JES2 does not free spool tracks allocated to the spin data set until the job is purged. In this case, end-of-task processing deallocates the data set and job purge processing returns the allocated tracks.

Spin Data Sets in the NJE Environment

JES2 transmits spin data sets separately from regular data sets. The SYSOUT receiver receives spin data sets as unique "jobs"; any later spin data sets or regular data sets cause the receiver to create a new job.

The SYSOUT receiver builds peripheral data definition blocks for the spin data sets in separate spin input/output tables, and the output processor builds separate spin output groups for them. If a regular (non-spin) data set has a copy count of 2 and the job has a copy count of 3, the data set should print 6 times. If a spin data set has a copy count of 2 and the job has a copy count of 3, the data set prints twice; job copy count does not apply to spin data sets.

System Data Set Characteristics

JES2 must also route JES2 system data sets generated during the execution of a program to an output device. To ensure that the messages and data appear together, you must describe all data sets for the job in a single output group. There are a number of ways to assign an output class to JES2 system data sets:

- The MSGCLASS= parameter of the job statement
- The JESDS= parameter on the JCL output statement
- The CLASS= parameter the JCL OUTPUT statement

The default for MSGCLASS= is the class specified on the JOBCLASS statement, or the class assigned to the device on which the job entered the system.

Note: Remember that all output grouping characteristics, not just class, must match to group system data sets with the output produced by the job.

Specifying JES2 Output Size Limits

At initialization, you can set a range of values which limits the number of output records or pages JES2 can process (by output group) on each local and remote printer or punch. Set this range of values in the device's initialization statement. You can alter this output control at processing time by using the LIM= parameter with the \$T command for line-mode data or the PLIM= parameter for page-mode data.

Variable Work Selection Criteria

The work selection criteria keyword (WS=) on the L(nn).ST(n), OFF(n).XX, PRT(nnnn), PUN(nn), R(nn).PR(n), and R(nn).PU(n) statements defines:

- The precise specification of job and output characteristics that JES2 considers when selecting work for an output device
- The order of importance (priority) of the selection characteristics
- The characteristics that JES2 must match exactly.

JES2 initializes the setup characteristics of a device based on the specifications supplied on a device (printer/punch) statement. JES2 groups a job's output data sets into output groups (job output elements) based on the data sets' output requirements. The user defines these requirements in the job's JCL or by JES2-supplied defaults.

When JES2 selects work for a device to process, JES2 compares the device's characteristics to the output requirements associated with the output groups waiting for processing. If JES2 finds an output group that matches the device's characteristics, JES2 routes the data sets associated with that output group to that output device.

If JES2 can not match an output group with a device, selection of the output group does not occur. The output group remains on the spool until the operator uses a \$T command to change an output device specification to match that output group. Alternatively, the operator can use the \$T O command to change the data set's

characteristics to allow the device to select the output group. If an output device selects an output group for processing, but certain setup characteristics do not match exactly, JES2 issues the \$HASP190 message notifying the operator of the characteristics that require changing.

Specifying Work Selection Criteria

The four criteria (Q,R,PRM, Volume), typically listed before the slash, also prioritize the lists they name. For example, on the PRT(nnnn) statement

```
PRMODE=(PAGE,UPL0T8,LINE)
```

specifies that the printer accepts PAGE-type output before UPL0T8-type output and UPL0T8-type output before LINE-type output. In fact, you must list PRM before the slash for printing to occur. If you specify Q, R, or V after the slash, JES2 will still match them exactly, but JES2 does not prioritize selection of their specification strings.

If the output group is a demand setup output group (refer to “Demand Setup and Output Data Set Grouping” on page 115), JES2 will not match those output groups whose output setup characteristics match the specific device setup. The match does not occur because demand setup indicates that the setup characteristics of individual job output elements can vary throughout the output group.

Determining the “Best” JOE

By using the JES2 work selection facility, you can add your own installation-defined work selection parameters. JES2 integrates these work selection parameters and those that JES2 provides [user specifications always override JES2 (HASP) table specifications] to build the work selection mask. The higher the mask value, the more likely a particular output group will receive **best JOE** status. The remainder of this section discusses the work selection processes and JES2 selection of the best JOE.

The following examples illustrate how JES2 allows the output device to select work. Refer to Table 20 on page 118 which presents a specific example of six output groups (job output elements) each of which relates to a particular job. In that figure:

- Output groups JOB5.1.1 and JOB53.6.2 are class A output on the class A output queue.
- Output groups JOB99.2.1 and JOB6.4.2 are class B output, on the class B output queue.
- Output groups JOB8.3.2 and JOB22.2.1 are class F output on the class F output queue.

Assume you have previously initialized three printers (using the PRT(nnnn) statements specified in Table 21 on page 118 through Table 26 on page 119); note the only difference between each statement is the WS= keyword character string specification. (The values shown next to the output groups listed, in Table 20 on page 118 for each printer are JES2-assigned values generated during the selection process.)

Table 20. Example of Six Output Groups on Output Queues

CLASS A QUEUE	
JOB5.1.1	JOB53.6.2
ROUTECD=LOCAL	ROUTECD=R3
PRIORITY=15	PRIORITY=10
FORMS=FMS1	FORMS=FMS1
FLASH=NONE	FLASH=NONE
FCB=STD6	FCB=STD6
UCS=AN	UCS=A11
PRMODE=LINE	PRMODE=UPLOT8
PAGECNT=0	PAGECNT=0
RECORDCNT=50	RECORDCNT=60
BURST	BURST
JOBNAME=TEST	JOBNAME=TEST
W=ABC	W=ABC
CLASS B QUEUE	
JOB99.2.1	JOB6.4.2
ROUTECD=R105	ROUTECD=R106
PRIORITY=01	PRIORITY=78
FORMS=FMS1	FORMS=FMS2
FLASH=TOPS	FLASH=CAPS
FCB=8LP1	FCB=8LP2
UCS=GF15	UCS=GF15
PRMODE=PAGE	PRMODE=PAGE
PAGECNT=90	PAGECNT=40
RECORDCNT=0	RECORDCNT=0
NOBURST	BURST
JOBNAME=TEST3	JOBNAME=TEST7
W=NONE	W=ABC
CLASS F QUEUE	
JOB8.3.2	JOB22.2.1
ROUTECD=LOCAL	ROUTECD=R3
PRIORITY=15	PRIORITY=78
FORMS=FMS2	FORMS=FMS3
FLASH=NONE	FLASH=NEWF
FCB=STD6	FCB=STD6
UCS=P11	UCS=GCF
PRMODE=U3800	PRMODE=UPLOT8
PAGECNT=0	PAGECNT=0
RECORDCNT=5000	RECORDCNT=1000
BURST	BURST
JOBNAME=TEST	JOBNAME=TEST7
W=ABC	W=NONE

Table 21. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue

A
PRT (1) BURST,CLASS=BAFGTD,FCB=8LP1,FLASH=TOPS,FORMS=FMS2, UCS=GF15,PRMODE=(PAGE,LINE,UPLOT8),W=ABC, LIMIT=(4000,8000),ROUTECD=(R3,LOCAL,R106,R105), PLIM=(40-80),WS=(W,R,Q,PRM,LIM/F,T,C,P)

Table 22. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue

WS=(W	R	Q	PRM	LIM	/	F	T	C	P)
JOB99.2.1	00									
JOB6.4.2	FF	FD	FF	FF	FF		FF	FF	00	78
JOB5.1.1	FF	FE	FE	FE	FF		00	00	00	15
JOB53.6.2	FF	FF	FE	FE	FF		00	00	00	10
JOB8.3.2	00									
JOB22.2.1	00									

Table 23. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue

B

PRT (2) BURST,CLASS=BAFGTD,FCB=8LP1,FLASH=TOPS,FORMS=FMS2,
UCS=GF15,PRMODE=(PAGE,LINE,UPL0T8),W=ABC,
LIMIT=(4000,8000),ROUTECD=(R3,LOCAL,R106,R105),
PLIM=(50-90),WS=(Q,R,PRM,LIM/P)

Table 24. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue

WS=(Q	R	PRM	LIM	/	P)
JOB99.2.1	FF	FC	FF	FF		01
JOB6.4.2	FF	FD	FF	00		78

Table 25. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue

C

PRT (3) BURST,CLASS=BAFGTD,FCB=8LP1,FLASH=TOPS,FORMS=FMS2,
UCS=GF15,PRMODE=(PAGE,LINE,UPL0T8),W=ABC,
LIMIT=(4000,8000),ROUTECD=(R3,LOCAL,R106,R105),
PLIM=(40-80),WS=(P,Q,R/PRM,LIM)

Table 26. Example Work Selection Criteria Specifications and Corresponding Values Assigned to Particular JOEs on the Output Queue

WS=(P	Q	R	/	PRM	LIM)
JOB6.4.2	78	FF	FD		FF	FF
JOB22.2.1	78	FD	FF		FF	00

JES2 scans each output class queue and compares the output groups on the queues to the printer's characteristics (DCT) as initialized on the PRT(nnnn) statement. Output group scanning/scheduling for PRT1 proceeds as follows: (Refer to Table 21 on page 118 through Table 26 on page 119(Use section A to assist your understanding of the selection process.)

1. Because class B has the highest priority on the CLASS= parameter specification for PRT(1), JES2 examines JOB99.2.1 on the class B queue first. The checking process stops almost immediately because the writer name

(W=NONE) specified for the output group does not match the writer name assigned to the printer (W=ABC). Writer name (W) appears before the slash, indicating an exact match must occur; because it does not match, JES2 assigns a value of 00 to this output group.

2. JES2 checks JOB6.4.2 next. All criteria before the slash matches; however JES2 assigns a value of FD to the destination (R) criterion. This value denotes a match two levels lower than the maximum priority (FF). Note that the ROUTECDE= keyword has set priority order as follows: R3, LOCAL, **R106**, R105. JES2 assigns a value of FFFDFFFFFFF0078 to this output group. This output group is now the current **best JOE** (that is, most likely to print).
3. Next, JES2 checks output group JOB5.1.1 in the class A queue because class A has priority after class B but before class F. Here again, all criteria specified before the slash matches; however, the destination (R), class (Q), and process mode (PRM) all receive a value of FE denoting a priority one level below the maximum (FF). The entire value obtained by this output group (FFFEFEFEFF00000015) is greater than that of JOB6.4.2 (see step 2 above). This output group then replaces JOB6.4.2 as the current **best JOE**.
4. JES2 now checks JOB53.6.2 in the class A. Again, all criteria specified before the slash matches; however, the class (Q) and process mode (PRM) receive a value of FE denoting one level below maximum due to their respective priority positions. The entire value obtained by this output group (FFFFFEFEFF00000010) is greater than that of JOB5.1.1 (see step 3 above). This output group now replaces JOB5.1.1 as the current **best JOE**.
5. The fifth output group JES2 checks is JOB8.3.2 in the class F queue. The scanning process stops because the process mode (PRM) for the output group (U3800) does not match that of the printer (PAGE, LINE, or UPLOT8). JES2 assigns a value of 00 to this output group.
6. Lastly, JES2 checks JOB22.2.1 in the class F. Here again, the scanning process stops immediately because the writer name (W=NONE) for the output group does not match that of the printer (ABC). Again, JES2 assigns a value of 00.

JES2 selects JOB53.6.2 as the best JOE for hardcopy output. The scanning process begins again when the output device is ready to select another output group, and JES2 determines the next **best JOE**.

To further illustrate how the ordering of the selection criteria can affect output selection, refer to and Table 20 on page 118 and Table 21 on page 118 through Table 26 on page 119(Section B) and review the following two examples:

1. The PRT(nnnn) statement for PRT2 lists the WS= keyword as WS=(Q,R,PRM/P). By putting the class (Q) criteria first in the WS list, JES2 searches for work one queue at a time. Note that JES2 selected JOB99.2.1 in the class B queue after scanning only two output groups. The next output group selected is JOB6.4.2. JES2 scans no other queues until it processes all selectable work on this queue.
2. The PRT(nnnn) statement for PRT3 lists the WS= keyword as WS=(P,Q,R/PRM,LIM). By putting the priority (P) first in the WS list, JES2 selects those jobs with the highest priority. (In the example, JOEs JOB6.4.2 and JOB22.2.1 both have a priority level of 78. JOE JOB6.4.2 is in the class B queue and JOE JOB22.2.1 is in the class F queue; therefore, because all other criteria before the slash match for both output groups, JES2 selects JOE JOB6.4.2, with the greatest value, as **best JOE**.

Tuning Work Selection Criteria

JES2 trace ID 20 tracks the number of output elements each device examines before finding selectable output. Use trace ID 20 records to determine the optimum settings for the WS= parameter. The \$TRACE output shows the effect of reordering the work selection list in terms of the amount of time spent and output examined for every queue search.

Table 27 illustrates table eight output groups on the output queues where the only relevant criteria are class, route code, and priority.

Table 27. Example of Output Groups on Output Queues

ROUTECD	A	CLASS B	C
LOCAL	JOE1	JOE3	JOE5 JOE7
R1	JOE2		
R2		JOE4 JOE6	
R3		JOE8	

The following general guidelines should help you tune your work selection parameters for the best performance. Evaluate these guidelines in regards to your specific environment.

- Remove irrelevant criteria. Criteria after the slash need not match. If a criterion is not important to you, remove it from the list. In particular, this applies to RJE devices where the only pertinent characteristics might be ROUTECDE (R) and CLASS (Q).
- Place WRITER (W) first in the list if there is a lot of output for a particular writer. This causes print/punch devices to reject work for a particular writer before examining any other criteria.

You can improve performance further by keeping electronic mail files in a separate class from other print/punch output. This prevents printers or punches from examining large amounts of mail when selecting work.

- Always place CLASS (Q) in the WS list. Leaving any criterion out of the list tells JES2 not to consider that criterion when examining output. If CLASS is not in the list, JES2 scans **every** class queue looking for output which matches all the other characteristics. To limit the number of queues scanned, include CLASS in the WS list, and limit the number of classes specified.

Using Table 27 as a reference for the output queues, Table 28 on page 121 illustrates the search results when CLASS is specified and when CLASS is not specified. The column "Output groups scanned" indicates how many output groups are examined before the device selects one to process. The column "Element selected" indicates which output group of those examined was selected.

Table 28. Search Results When Specifying CLASS

WS Criteria	Order of Selection	Output groups scanned	Element selected
WS=(Q,R) Q=BC R=(R2,Local)	JOE4	2	2
	JOE6	2	2
	JOE3	2	1
	JOE5	3	2
	JOE7	2	2

Table 28. Search Results When Specifying CLASS (continued)

WS Criteria	Order of Selection	Output groups scanned	Element selected
WS=(R) R=(R2,Local)	JOE4	4	4
	JOE6	4	4
	JOE1	6	1
	JOE3	5	2
	JOE5	4	3
	JOE7	3	3

In Table 28, JOE1 is selected when WS=(R) is specified because all class queues are examined. JOE1 is not selected when WS=(Q,R) is specified because only queues B and C are examined.

Assume JOE4 and JOE6 have been selected first because their routecode was a best match. They are longer no longer on the queues.

When WS=(R) JES2 searches the queue for work as follows:

- JOE1 has a ROUTECDE=LOCAL which is not a best possible match
 - Starting with CLASS=A
 - JOE2 has a ROUTECDE=R1 which does not match at all
 - Continue searching on next queue
 - Go to CLASS B:
 - JOE3 has a ROUTECDE=LOCAL. It is not the best possible so continue looking
 - JOE8, the ROUTECDE does not match at all
 - Go to CLASS C:
 - JOE5. It is not the best possible and not better than JOE3. Continue searching.
 - JOE7. It is not the best possible and not better than JOE3
 - All JOEs have been examined
 - JOE3 is selected because it is the best one found.
- Give CLASS (Q) a higher priority than other criteria, particularly ROUTECDE (R). This improves performance by reducing the amount of output examined. When CLASS has a higher priority than ROUTECDE (farther to the left in the list), JES2 prints all eligible work from the first class queue before moving on to the next class. If CLASS has a lower priority, JES2 might unsuccessfully search every class queue, and possibly every output element, looking for a perfect match. The following illustrates the search results when CLASS is before ROUTECDE and when CLASS is after ROUTECDE.

Table 29. Search Results When Specifying CLASS before ROUTECDE

WS Criteria	Order of Selection	Output groups scanned	Element selected
WS=(Q,R) Q=ABC R=(Local,R1,R2)	JOE1	1	1
	JOE2	1	1
	JOE3	1	1
	JOE4	3	1
	JOE6	2	1
	JOE5	2	2
	JOE7	2	2
WS=(R,Q) Q=ABC R=(Local,R1,R2)	JOE1	1	1
	JOE3	2	2
	JOE5	5	5
	JOE7	5	5
	JOE2	4	1
	JOE4	3	1
	JOE6	2	1

- Give careful consideration to PRIORITY (P) in the work selection list. If CLASS (Q) is before the slash in the list, then placing PRIORITY after CLASS has no effect and adds unnecessary overhead to JES2 because the class queues are already in priority order.

Placing PRIORITY (P) before CLASS (Q), and before the slash, causes JES2 to look for the highest priority piece of output in the system. This results in long searches while JES2 examines every piece of output looking for the highest priority work.

The following illustrates the search results when specifying PRIORITY and when PRIORITY is not specified.

Table 30. Search Results When Specifying PRIORITY

WS Criteria	Order of Selection	Output groups scanned	Elements selected
WS=(Q,R) Q=ABC R=(R2,Local)	JOE1	2	1
	JOE4	3	3
	JOE6	3	3
	JOE3	3	2
	JOE5	4	3
	JOE7	3	3
WS=(P,Q,R) Q=ABC R=(R2,Local)	JOE1	8	1
	JOE3	7	2
	JOE4	6	2
	JOE5	5	4
	JOE6	4	2
	JOE7	3	3

- If you include JOBname in the WS list, it causes JES2 to gather all output for a job and attempt to process that output consecutively. The JOBNAME= parameter for a particular device determines what job name JES2 selects once JES2 has processed all output that matches the current job name.
 - If JOBname= is specified before the slash in the WS= list:

JES2 selects only those jobs that match the value specified on JOBNAME= for a specific device. When JOBNAME= is specified as a generic name, JES2 only processes jobs that match that pattern and attempts to process all output for that job name consecutively.

- If JOBname= is specified after the slash in the WS= list:

JES2 uses the value specified on JOBNAME= to select new job names for the specific device. If there are no job names that match the JOBNAME= specification, JES2 selects jobs as if JOBname were not listed in the WS= list. A device gathers and processes all output for a particular job before again examining the value specified on JOBNAME= for more jobs.

If you require JES2 to group jobs based on job name but do not want JES2 to prefer a particular JOBNAME= pattern, specify JOBNAME=* on the device statement and code JOBname after the slash in the WS= list.

Notes:

1. Use a \$T *devname*,JOBNAME=*jobname* command to stop processing jobs of the current JOBNAME= specification and begin searching for jobs of the new name.
 2. Specifying JOBNAME in the WS list causes JES2 to examine all output while gathering output for a job and finding job name matches. This causes performance degradation.
- If your installation has many active remote devices, minimize the number of queue elements searched by spreading the output for different remotes over multiple classes.

Many RJE devices that share the same class queue unnecessarily search a large queue of output destined for other remotes.

Carefully consider all work selection settings. Specifying the WS list incorrectly or inappropriately causes exhaustive searches of the JES2 output queues and excessive processing.

Output Disposition for SYSOUT Data Sets

JES2 lets you use several initialization statements to specify how JES2 should process a SYSOUT data set when the SYSOUT data set is eligible for selection. You can base the processing on the successful execution of a job or task. The user can alter these specifications through JCL.

Specifying Output Disposition

You can specify default output dispositions for groups of output by coding the OUTDISP=parameter on any of the following initialization statements.

- JOBCLASS(v) for system output associated with started tasks, time sharing users, and batch jobs in a specific JOB class. (For example: JES2 system data sets for batch jobs, the JES job log.)

Note: Only code OUTDISP= on JOBCLASS when you require that system data sets have a specific output disposition regardless of their message class (MSGCLASS=) specification. If you have no such requirement, either code OUTDISP=() or leave it off the JOBCLASS statement completely.

- OUTCLASS(v) for all batch SYSOUT (other than JES2 system data sets)

The OUTDisp= parameter has the format:

OUTDisp=[() [normal disposition] [,abnormal disposition] ()]

Figure 16. The OUTDisp= Parameter

The *normal disposition* subparameter specifies the disposition for the output if the job completes normally. JES2 chooses the normal disposition when the job's JCL contains no errors, the job does not abend, and the COND= parameter on the JCL JOB statement does not cause the job to fail. The *abnormal disposition* subparameter specifies the disposition for the output if the job does not complete successfully.

Note: The disposition for spin output is determined at the time that the output is spun; it does not change if a job fails later. The OUTDisp= parameter allows you to specify the following dispositions:

HOLD Hold the output. JES2 does not process the output until you either change the disposition to WRITE or KEEP, or release the output. When the output is released, the disposition changes to WRITE.

KEEP Process the output and then keep a copy of it on spool. After processing, the disposition of this output becomes LEAVE.

LEAVE
JES2 does not process the output until you change the disposition to either WRITE or KEEP, or release the output. When the output is released, the disposition changes to KEEP.

PURGE
Purge the output immediately.

WRITE
Process the output then purge it.

Table 31 on page 125 shows the defaults for output dispositions based on what you code.

Table 31. JES2 Defaults for the OUTDISP Parameter

If You Code:	JES2 Assumes:
No OUTDisp	OUTDisp=(WRITE,WRITE)
Normal end disposition only For example: OUTDisp=HOLD	Both values will be the one you specified for normal end. As in the example: OUTDisp=(HOLD,HOLD)
Abnormal end disposition only For example: OUTDisp=(,KEEP)	The value of the normal end disposition will be WRITE, while the abnormal end will be the value you gave it. As in the example: OUTDisp=(WRITE,KEEP)
Both the normal and abnormal end dispositions For example: OUTDisp=(PURGE,HOLD)	They will both assume the values you coded. As in the example: OUTDisp=(PURGE,HOLD)

Overriding Output Disposition

For a particular SYSOUT data set, a user might need to change the default output disposition that was set by initialization statements. The user can override the defaults through one of the following:

- JCL statements
- TSO/E commands
- Operator commands

Changing Output Disposition Through JCL: The user can override output disposition through JCL either by coding HOLD=YES on a DD statement that defines the SYSOUT data set or by coding an OUTDISP= parameter on an OUTPUT JCL statement associated with a SYSOUT data set. Specifying HOLD=YES on the DD statement forces JES2 to treat the SYSOUT as if OUTDISP=(HOLD,HOLD) appears on an OUTPUT JCL statement associated with the SYSOUT.

Changing Output Disposition Through TSO/E: When a user views held output using the TSO/E OUTPUT command, the user can choose to release the data set. Releasing the output would change the disposition of the output from HOLD to WRITE or from LEAVE to KEEP. Only output whose disposition, when the job executed, was HOLD or LEAVE **and** whose disposition has not been modified is eligible for TSO/E OUTPUT command processing. See *z/OS TSO/E Command Reference* for more information about releasing output when using the TSO/E OUTPUT command.

Changing Output Disposition Through Operator Commands: Use the \$O (output) operator command to release output if it is HOLD or LEAVE, or use \$T O to change the disposition of output to another disposition. You can use these commands to change the disposition of all output based on the time elapsed (n days or n hours) since a job created the output. Changing held output's disposition based on its age releases spool space occupied by output that is no longer needed. For more information on the \$O command, see *z/OS JES2 Commands*.

JES2 overrides output dispositions in the following order:

1. HOLD= on the DD statement
2. OUTDisp=(normal,abnormal) on the OUTPUT JCL statement
3. OUTDisp=(normal,abnormal) on the JOBCLASS initialization statement, for JES2 system data sets
4. OUTDisp=(normal,abnormal) on the OUTCLASS JES2 initialization statement.

You should use OUTDisp= on the initialization statements to set up default dispositions: usually WRITE for normal disposition and some form of hold for abnormal disposition. If you need to change a disposition for a specific job, use OUTDisp= on the OUTPUT JCL statement.

JES2 keeps a record of the time a job creates output. Use the OUTTIME= parameter on the OUTDEF statement to control whether or not JES2 changes the creation time of the output to the current time when you change any characteristics of the output. See *z/OS JES2 Initialization and Tuning Reference* for the syntax of the OUTDEF statement.

Purging JES2 System Data Sets

JES2 purges system data sets if CONDPURG=YES is specified on the JOBCLASS initialization statements and the job produced no output data sets (or the output disposition of all the system data sets was PURGE). If both conditions are not met, JES2 system data sets obtain their output disposition from the OUTDisp= parameters specified explicitly on the JOBCLASS initialization statements. If

OUTDisp= is not specified on the JOBCLASS initialization statements, JES2 uses the disposition specified on the OUTCLASS(n) initialization statement for that message class.

Note: The CONDPURG= parameter **does not** apply for jobs that did not complete successfully.

Offloading and Reloading SYSOUT Based on Output Disposition

During a spool offload or reload operation, you can select SYSOUT with specific output dispositions for JES2 to offload or reload, by specifying OUTDisp on the WS= parameter and the OUTDisp= parameter on either the OFF(n).ST or OFF(n).SR initialization statement. For example,

```
OFF(1).ST      ...,
               OUTDisp=(KEEP),WS=(,OUTDisp)
```

Figure 17. Example of OUTDisp as a Work Selection Criteria

causes the offload SYSOUT transmitter for offload device 1 to offload only SYSOUT with an OUTDisp of KEEP. “Variable Work Selection Criteria” on page 116 and “Spool Offload Facility” on page 178 describe the WS=parameter and the spool offload facility.

Changing Output Disposition During Reload: Specifying MOD=(OUTDisp=disposition) on the OFF(n).SR statement causes JES2 to change the output disposition of SYSOUT selected during the reload process.

Transmitting Output to Another Node

When JES2 transmits output to another node, JES2 indicates the output's disposition in the network header. If the receiving node has a level of JES2 SP Version 4 or Version 5 installed, the receiving node keeps the disposition set by the transmitting node. Otherwise, the receiving node will recognize the data as non-held if the disposition set by the transmitting node was WRITE. If the disposition set by the transmitting node was HOLD, KEEP, or LEAVE, then the receiving node will recognize the data as held.

When a node with JES2 SP Version 4 or Version 5 receives output from a node with a previous level of JES2 installed, the JES2 SP Version 4 or Version 5 member assigns an OUTDisp of HOLD to the output if the data was held. If the output was non-held, the JES2 SP Version 4 or Version 5 member assigns an OUTDisp of WRITE to the output.

Automatic Restart Management

Automatic restart management is an MVS recovery function that can improve the availability of specific batch jobs or started tasks. When a job or task fails, or the system on which it runs fails, automatic restart management can restart the job or task without operator intervention. To be eligible for restart under automatic restart management, a batch job or started task must register with automatic restart management. See *z/OS MVS Setting Up a Sysplex* for information on setting up automatic restart management and see *z/OS MVS Programming: Sysplex Services Guide* for more detail on how MVS in a sysplex controls job's under automatic restart management.

The following JES2-specific items need consideration when using automatic restart management:

- When a job or system fails and the job is restarted by automatic restart management, all non-spin SYSOUT data sets created during the previous execution are deleted.

If you desire to make a SYSOUT data set available for JES2 output service processing when the data set is closed, you need to use the FREE=CLOSE JCL option for the corresponding dynamic allocation option. Automatic restart management does not delete such data sets when the job is restarted.

If you need to retain a SYSOUT data set that was still open and not yet closed at the time of failure, you need to use the SPIN=UNALLOC JCL option (or corresponding dynamic allocation option). Using this option causes the data set to be unallocated and made available to JES2 at job termination time (that is, when the job or system initially fails and the job is restarted).

The following table summarizes the use of the FREE=CLOSE and SPIN=UNALLOC JCL options and the effect they have on SYSOUT data created by automatic restart management - registered jobs.

Option Used	SYSOUT Data Set Status at Time of Restart by automatic restart management	JES2 Processing
FREE=CLOSE	Closed	The data set is unallocated and spun-off when closed by the job.
FREE=CLOSE	Open	JES2 deletes the data set.
SPIN=UNALLOC	Closed	The data set is unallocated and spun-off at job termination.
SPIN=UNALLOC	Open	The data set is unallocated and spun-off at job termination.
FREE=CLOSE and SPIN=UNALLOC	Closed	The data set is unallocated and spun-off when closed by the job.
FREE=CLOSE and SPIN=UNALLOC	Open	The data set is unallocated and spun-off at job termination.

Note: SYSOUT data sets created and maintained by JES2 (for example, JESMSG LG, JESYSMSG, JESJCL) are not deleted when a job is created by automatic restart management.

- You cannot use JES2 spool offload to offload jobs that are waiting for restart by automatic restart management.

Dividing Output into Smaller Units

Applications can decrease the turn-around time of large amounts of printed outputs that jobs create by specifying the SEGMENT= parameter on the DD JCL statement that defines the output for line mode data. SEGMENT= forces JES2 to spin off output after producing a specified number of pages. There will be a segment identifier on the separator page for each segment if segmentation is in effect. See *z/OS MVS JCL Reference* for more information on specifying the SEGMENT= parameter.

Segmenting output into many small pieces, however, could cause performance problems as each segment requires an output group to represent it. Specifying

SEGLIM= on the OUTDEF initialization statement minimizes the impact output segmentation has on your installation. When the number of segments a job creates for any piece of output exceeds the SEGLIM= value, JES2 stops segmenting the output and prints the remaining output as one segment. See *z/OS JES2 Initialization and Tuning Reference* for additional information about the OUTDEF statement.

If a SYSOUT data set is segmented, each segment is treated as a separate file for printing, punching, or NJE transmission. Output segmentation can be used to make portions of the SYSOUT data set available earlier for processing or transmission before the job completes or before the entire data set is available. For NJE transmission, this can also improve line utilization by reducing the time to re-transmit files over NJE should there be a line failure or other unrecoverable error.

Defining Output Limits

There are several ways in which an installation can set job output limits and define the actions that JES2 takes when a job exceeds those limits. For example:

- You can specify defaults in the JES2 initialization stream that limit the number of bytes, cards, lines, or pages that batch jobs or APPC transaction programs can generate before JES2 initiates some predefined action, such as canceling the job, canceling the job with a dump, or issuing a warning message to the operator. You can use the following initialization statements to set installation-wide job output limits:

Statement

Purpose

ESTBYTE

Estimated spool utilization for output exceeded

ESTLNCT

Default estimated print output and options

ESTPAGE

Default estimated page output exceeded

ESTPUN

Default estimated punch output and options

- You can implement JES2 installation Exit 9 to make decisions when output exceeds output limits. For APPC transaction programs, JES2 Exit 43 can be used to override SYSOUT limits. See *z/OS JES2 Installation Exits* for information about these exits.
- For individual batch jobs, end users can define output limits by specifying output limits on the JCL JOB statement or the JECL /*JOBPARM statement.

If more than one of the methods listed above are being used to set output limits, JES2 uses a predefined order of overrides to determine which output limits and resulting system actions to honor. The order of overrides differ depending on whether the job is a batch job or a transaction program.

For batch jobs, JES2 uses the following order of overrides:

- JES2 initialization stream
- JECL /*JOBPARM statement (overrides the initialization stream)
- JCL JOB statement (overrides the /*JOBPARM JECL statement)

For output produced by transaction programs, JES2 uses the following order of overrides:

- JES2 initialization stream (lowest level)
- JES2 Exit 43 (overrides the initialization stream)
- JCL JOB statement (overrides JES2 Exit 43)

See *z/OS JES2 Installation Exits* for information about Exit 43.

The following example demonstrates the order of overrides when using the JCL JOB and JECL /*JOBPARM statements:

```
ESTBYTE NUM=9999
ESTLNCT NUM=2
ESTPAGE NUM=40
ESTPUN  NUM=100
```

Figure 18. Sample Initialization Stream Definitions

```
//MRECKSA JOB MARTY,...,PAGES=200,BYTES=20000
/*JOBPARM      LINES=100,BYTES=10000
//STEP1 EXEC PGM=IEBDG
```

Figure 19. Sample JCL with Output Limits

In the example shown above, the following output limits would exist:

- The batch job is limited to 20,000,000 bytes (20000x1000 - because the byte definition is in thousands). The BYTES= keyword on the JOB card overrides the JECL /*JOBPARM and the initialization statement default (ESTBYTE statement).
- The batch job is limited to 100,000 lines (100x1000 - because the line definition is in thousands). The value from the /*JOBPARM statement is used because it overrides the initialization stream default (ESTLNCT statement) and the LINES keyword is omitted on the JOB card.
- The batch job is limited to 200 pages. The value specified on the PAGES= keyword on the job card overrides the initialization stream default (ESTPAGE statement).
- The batch job is limited to 100 cards. The limit is taken from the ESTPUN initialization statement because no override value exists on the JCL JOB or JECL /*JOBPARM statements.

If a batch job or APPC transaction program exceeds the output limits set by JES2, JES2 issues message \$HASP375. However, you can use JES2 Exit 9 to specify what action(s) should be taken if a job exceeds output limits. See *z/OS JES2 Installation Exits* for information about Exit 9.

See *z/OS MVS JCL Reference* for additional information about specifying output limits on JCL JOB or JECL /*JOBPARM statements. See *z/OS JES2 Initialization and Tuning Reference* for additional information about the ESTBYTE, ESTLNCT, ESTPAGE, and ESTPUN initialization statements.

Considerations for Started Tasks and TSO LOGONs

Output limits for TSO/E transmits can be set by TSO/E using the TSO/E OUTLIM= parameter. JES2 also sets a limit internally. When SYSOUT is transmitted in the foreground for started tasks and TSO/E LOGONs, the member uses the lower of these two limits. JES2 sets the following output limits for started tasks and TSO LOGONs:

- 999,999 for lines, cards, and pages
- 2,147,483 (in 1000s of bytes) for spool utilization.

An installation can change the limits for started tasks or TSO LOGONs by using JES2 Exit 20 to change the limit for each particular started task or TSO LOGONs. The limit for TSO/E transmits which are specified through the OUTLIM parameter, should not be greater than the limit JES2 sets for punches or a X'722'abend will occur. See *z/OS TSO/E Customization* for information about limiting the TSO/E TRANSMIT command.

JES2-Provided Client Print Services

JES2 provides client print services by allowing applications such as the IBM z/OS Print Server to allocate space on JES2 spool for print jobs submitted from workstations in the TCP/IP network.

Print jobs that use print services can take advantage of traditional JES2 print services. These include work selection and work balancing across logical printer groups, use of JES2 default SYSOUT attributes, SYSOUT processing progress and monitoring, and SYSOUT cancelling, holding, and releasing.

JES2 provides these client print services in a manner compatible with its standard operational characteristics. For example, client print services can:

- Query their jobs to determine status, as does the JES2 operator
- Set jobs priorities consistent with JES2 priority values, and validate that a job can print on JES2 queues
- Use the SYSOUT application programming interface (SAPI).

Printers and Punches

An operator responds to a request for a setup change following a \$HASP190 message by doing one of the following:

- Performing the setup requested, then issuing the \$S command to the device.
- Allowing the use of the setup only for the data set group that requests it, by issuing the \$P command, followed by the \$S command. The \$P command causes the device to stop after printing the current data set group.
- Forcing an alternate setup on this data set group by issuing the \$T command, followed by the \$S command. The operator must set up the device, however, and must repeat the \$T and \$S commands for each data set in the group. JES2 considers header and trailer pages data sets for this sequence.
- Causing the selection of an alternate data set group by holding (\$H command) the job, and then issuing the \$I or \$E command, which requeues the data set group in a held state. The operator must later release the held group.
- Deleting the data set group by issuing the \$C command to the device. The device then selects another data set group for the setup or requests another setup.

Print Chain Alias for 1403 and 3211 Printers

The system assigns an alias for each installation's standard print chain not defined on a given 1403 or 3211 printer. This alias provides JES2 with flexibility in scheduling printers for SYSOUT data sets. For example, a request for the 1403 TN train would be assigned the T11 train, if the data set prints on a 3211. Table 32 on page 132 lists the assigned aliases, which follow the naming conventions currently used in SYS1.IMAGELIB.

Table 32. Assigned Alias Names for the 1403 and 3211 Printer Chains

Image	Alias
UCS1AN	UCS1A11
UCS1HN	UCS1H11
UCS1PN	UCS1P11
UCS1TN	UCS1T11
UCS2A11	UCS2AN
UCS2H11	UCS2HN
UCS2P11	UCS2PN, UCS2RN, UCS2QN
UCS2T11	UCS2TN

The image and aliases are included in SYS1.IMAGELIB at system installation.

Some trains, such as SN and G11, do not have aliases because they have no equivalent train on another printer. An installation can assign an alias if it so chooses. (See *MVS/DFP Linkage Editor and Loader* for details about the ALIAS statement.) JES2 uses any aliases supplied. If no alias is available, you should use an installation-defined SYSOUT class or a printer routing code (specified by the DEST parameter) to assign the data set to the correct printer. JES2 notifies the operator when you direct it to print a data set on a printer for which the proper image does not exist, if you have not used a SYSOUT class or printer routing code. The operator can then print the data set with a valid train or redirect the data set to the proper printer by using the JES2 \$E command.

3211 Indexing

JES2 supports 3211 indexing through the specification of the INDEX parameter on the /*OUTPUT control statement, JCL OUTPUT statement, or in the extended FCB image. With the extended FCB image, JES2 supplies two special FCBs: FCB26 for 6 lines per inch and FCB28 for 8 lines per inch (specified as FCB=6 and FCB=8, respectively). These FCBs contain a channel 1 indication in position 1, a special index flag in the third byte, and the number of lines per inch in the fourth byte of the image. The special index flag in the third byte of FCB26 and FCB28 contains X'80' plus a binary index value, in the range of 1 to 32 (if not specified, 1 is the default). The index value sets the left margin (1 indicates flush-left position; other values cause indentation of the print line by n-1 positions).

For JES2 to use any other FCB images, they must specify channel 1 in position 1; otherwise, JES2 incorrectly positions the forms in the printer. (STD1 and STD2 do not specify channel 1 in position 1, therefore, you should not specify these for JES2 unless you alter them.) If the third byte of any other FCB image contains a data character (specifying the number of lines per inch) other than X'80', JES2 uses that specification and supplies an index value of 1.

Defining the Advanced Function Printer (Using the PRT(nnnn) Statement)

JES2 supports Advanced Function Printing (AFP) printers (such as the 3800 model 3 executing in full function mode) as local printers only. A 3800 model 3 running in compatibility mode is functionally equivalent to a 3800 model 1.

Specify a printer to operate under the control of a single functional subsystem by using the FSS= keyword on the JES2 PRT(nnnn) initialization statement. You must define each functional subsystem (and the printer(s) under its control) individually so you can access the functional subsystem applications (FSA) separately and use

separate PROCLIB procedures for each functional subsystem (FSS). (Refer to “Defining a Functional Subsystem for Advanced Function Printing (Using the FSS(accccccc) Statement)”.)

You can start a 3800-3 printer running under the control of either JES2 or a functional subsystem. Other AFP printers must be run under the control of an FSS. To do this, set the MODE= keyword on the PRT(nnnn) initialization statement to either JES or FSS as appropriate.

The following affects how JES2 sets the MODE= parameter. Note that all parameters referred to belong to the PRT(nnnn) initialization statement.

- If you specify MODE=JES, MODE is set to JES unless you also specify an FSS procedure name (FSS=fssname) and the unit address (UNIT=) of an AFP1 unit control block (UCB). Then MODE=FSS.
- If you specify MODE=FSS, MODE is set to FSS unless you fail to specify an FSS.
- If you do not specify the MODE= parameter:
 - MODE= defaults to JES if you do not define an FSS procedure name.
 - MODE= defaults to JES if you define an FSS procedure name and a unit address that does not point to an AFP1 UCB.
 - MODE= defaults to FSS if you define an FSS without specifying the a unit address.
 - MODE= defaults to FSS if you define an FSS and the unit address of an AFP1 UCB device.

Note: If you do not specify the UNIT= parameter for a MODE=JES printer, you must use the \$T PRT(nnnn) command to specify a unit address (UNIT=) before you can start the printer through a \$S PRT(nnnn) command.

Specify a procedure in one of the started task procedure libraries on SYS1.PROCLIB through the PROC= keyword on the FSS(accccccc) initialization statement. This procedure must contain the JCL needed to start the functional subsystem. JES2 starts the indicated functional subsystem with a name of procname.fssname (where the fssname is the subscript on the FSS(accccccc) statement).

As system requirements change, you can use the \$T PRTnnnn command to alter the initial setting of the printer. Some cases require you to drain the functional subsystem before issuing the \$T command; other cases do not. This requirement is printer-specific.

Defining a Functional Subsystem for Advanced Function Printing (Using the FSS(accccccc) Statement)

Associate an FSS with an AFP printer such that the device receives the necessary FSA support. Use the FSS(accccccc) initialization statement to define an FSS to JES2 and associate the JES2 device to the required FSS and corresponding FSA.

- Use the subscript (accccccc) on the statement FSS(accccccc) to define a functional subsystem token. Then specify this token on the PRT(nnnn) statement through the FSS= parameter to associate the device with the appropriate FSS.
- Specify the name of the JES2 functional subsystem support load module name if it is different from HASPFSSM (the default) through the HASPFSSM= parameter. Ensure that the functional subsystem that you define can access the proper JES2 functional subsystem support load module that you require. This process

might require a STEPLIB in the functional subsystem procedure to override the default load module name, HASPFSSM, on the FSS(accccccc) initialization statement. Note that the HASPFSSM load module resides in SYS1.VnRnMn.SHASLINK.

Using Advanced Function Printing Printers

You can operate Advanced Function Printing printers only under the control of a functional subsystem and managed by a print services facility (PSF). Except for a 3800-3, you **cannot** operate an AFP printer in compatibility mode; JES2 will not permit you to change the operation of an AFP printer to compatibility mode.

You can define a 3800-3 printer as running in either **full-function mode** and thereby capable of accepting “page” or “line” as the addressable unit of output or in **compatibility mode** with “line” as the addressable unit of output.

Compatibility-Mode Support

Although a page-mode printer is capable of printing either output type, a line-mode printer cannot process page-mode data.

A 3800-3 (which is an AFP printer) when running in **compatibility mode** is functionally equivalent to 3800-1 printers (which are line-mode printers). You need define no special address spaces or have any other special considerations when running a 3800-3 in compatibility mode. JES2 supports a 3800-3 running in compatibility mode as if it were a 3800-1. Figure 5 on page 66 provides an example of the JES2 initialization statements required to support a 3800-3 in either full-function or compatibility-mode.

Full-Function Mode Support

Full-function mode is using those functions of the printer that produce page-mode output. The concept of **page-mode** permits printed pages to contain both text data and graphical presentations. Page-mode printers allow for the specification of complex data attributes not available from printers without all-points-addressable capabilities. The user can define and request such attributes as:

- **Segments** - predefined portions of a page
- **Overlays** - predefined page templates
- **Images** - pictures and graphics
- **Type fonts** - collections of unique or stylized print characters.

The graphical material can include a wide range of print font types and sizes [1/18 inch (4 pts.) to 1/2 inch (36 pts.)] for use in text headings, logos, and imbedded artwork; shading of textural and user-produced graphics; and graph plotting. You can make the above print features available for page-mode printing by defining AFP printers as a page-mode printers.

The advanced function printing data stream (AFPDS) used in IBM page-mode printing does not allow the use of blank truncation within the data stream. Be certain that the output class that you define for the use of advance function printing (AFP) does not specify blank truncation. Specify BLNKTRNC=NO on the OUTCLASS statement; the JES2 default is BLNKTRNC=YES.

JES2 does not communicate directly with an AFP printer but rather through the functional subsystem interface (FSI) to an FSS. The FSI defined for an FSS specifies the manner in which the FSS/FSA and JES2 communicate. IBM designed a specific FSS/FSA, the Print Services Facility, to support the AFP printer. Refer to “Functional Subsystem Support” on page 65 for a more detailed description and Figure 5 on page 66 for a pictorial description of these relationships.

Route data sets that include both page-mode and line-mode data to page-mode printers exclusively, and define the data sets as page-mode on the JCL OUTPUT statement. JES2 provides job output routing, through the printer work selection criteria (WS= parameter the PRT(nnnn) statement). To define an AFP printer as page-mode, also specify PRMODE=(PAGE,...) on the PRT(nnnn) statement.

Functional subsystem support of a page-mode printer applies to all page-mode printers in a multi-access spool JES2 complex. Therefore, both you and the operator need to be aware of what printers in your complex can process of which type of work at any one time. Table 33 summarizes this output processing support by printer type.

Table 33. Summary of Data Type and Printer Mode Compatibility

DATA PROCESS MODE (PRMODE)	PRINTER PROCESS MODE (PRMODE)
	PAGE-MODELINE-MODE*
LINE	YES**YES
PAGE	YESNO***

* A page-mode printer operating in 3800 compatibility mode is equivalent to a line-mode printer.

** This assumes the printer is defined to accept line mode data, that is, PRT(nnnn) PRMODE=(LINE,PAGE...)....

*** If the operator forces a line-mode printer to print a page-mode data set, the data set will print with undesirable results.

Creating Output for a 3540 Diskette Writer

A SYSOUT data set to be written to a 3540 diskette *must* be written by a diskette writer, which is an external writer. You can write to a 3540 diskette through the following parameters on a JCL DD (data definition) statement:

- Specifying DSID= to indicate the data set identifier.
- Specifying SYSOUT= to indicate an output class or the diskette writer process.

See *z/OS MVS JCL Reference* for more information on both the DSID= and the SYSOUT= parameter of the DD statement. See *OS/VS2 IBM 3540 Programmer's Reference* for details on the diskette writer.

The JES2 Print Separator

The JES2 print/punch processor writes separation records (pages or cards) prior to writing the output of each job. These separation records make it easy to identify and separate various job outputs written contiguously on the same printer or card punch device. The separator appears at the beginning and the end of a job's output or at the beginning of interrupted (continued) output.

The print separator consists of a detail box and, optionally, the jobname and jobid in block letters. Use the SEPPAGE= parameter of the PRINTDEF initialization statement to specify whether or not JES2 produces the print separator page and to specify the format of the print separator page for all local and remote printers. *z/OS JES2 Initialization and Tuning Reference* contains the syntax of the SEPPAGE= parameter. Figure 20 on page 136 shows an example of a complete START print separator page.

```

JJJJJJJJJ 000000000 BBBB BBBB 000000000 1
JJJJJJJJJ 00000000000 BBBB BBBB 00000000000 11
JJ 00 00 BB BB 00 000 111
JJ 00 00 BB BB 00 0000 1111
JJ 00 00 BB BB 00 00 00 11111
JJ 00 00 BBBB BBBB 00 00 00 11
JJ 00 00 BBBB BBBB 00 00 00 11
JJ 00 00 BB BB 00 00 00 11
JJ JJ 00 00 BB BB 0000 00 11
JJ JJ 00 00 BB BB 000 00 11
JJJJJ 00000000000 BBBB BBBB 00000000000 11
JJJJJ 000000000 BBBB BBBB 000000000 11

JJJJJJJJJ 000000000 BBBB BBBB 000000000 1 1 1 1
JJJJJJJJJ 00000000000 BBBB BBBB 00000000000 11 11 11 11
JJ 00 00 BB BB 00 000 111 111 111 111
JJ 00 00 BB BB 00 00 00 1111 1111 1111 1111
JJ 00 00 BBBB BBBB 00 00 00 11 11 11 11
JJ 00 00 BBBB BBBB 00 00 00 11 11 11 11
JJ 00 00 BB BB 00 00 00 11 11 11 11
JJ JJ 00 00 BB BB 0000 00 11 11 11 11
JJ JJ 00 00 BB BB 000 00 11 11 11 11
JJJJJ 00000000000 BBBB BBBB 00000000000 11 11 11 11
JJJJJ 000000000 BBBB BBBB 000000000 11 11 11 11

***START*****START*****START*****START*****START*****START*****START*****START***
*
* JOBID: JOB01111 *
* JOB NAME: JOB01 *
* USER ID: Z00T *
* SYSOUT CLASS: A *
* OUTPUT GROUP: GRP01.CLASSA.D3289 *
* TITLE: Corporate Checking Account History *
*
* DESTINATION: NEW YORK *
* NAME: DB Pizzuto *
* ROOM: 2G-54 *
* BUILDING: Textile Building *
* DEPARTMENT: Accounting *
* ADDRESS: 999 W. 99th Street *
* New York, New York *
* 10000 *
* 212-555-3487 *
*
* PRINT TIME: 13:47:13 *
* PRINT DATE: 25 SEP 1993 *
* PRINTER NAME: PRT2 *
* SYSTEM: IBM1 *
*
***START*****START*****START*****START*****START*****START*****START*****START***

```

Figure 20. Sample JES2 Print Separator Page

After defining the global separator page options through the PRINTDEF statement, you can suppress production of the separator page by specifying SEP=NO on the PRT(nnnn) or R(nnnn).PR(m) statements, or through the use of an Exit 1 routine.

The user can supply the information JES2 uses to build the separator page in either the OUTPUT JCL statement or the JOB JCL statement. See *z/OS MVS JCL*

Reference for the parameters of the OUTPUT and JOB statements. The following fields can also be modified through SDSF while output resides on the output or hold queue:

- ADDRESS
- BUILDING
- DEPARTMENT
- NAME
- ROOM
- TITLE

Modifying the JES2 Print Separator

The IBM-defined installation exit, Exit 1, allows you to provide an exit routine to control production of the standard separator page or to create your own separator page to replace or print with the standard separator page. Additionally, the IBM-defined installation exit, Exit 23, allows you to provide exit routines to control production of a job separator page for page-mode printers. This exit allows only separator page suppression or modification of the FSI job separator page area (JSPA) control block used to build the separator page. Print Services Facility creates the separator page.

JES2 writes the separator pages before and after processing the output that one output group represents. You can create separator pages for each data set, or a copy of each data set, by enabling Exit 15 (Output Data Set/Copy Separators). If you do not enable Exit 15, JES2 prints separator pages only for the start and end of an output group. Refer to *z/OS JES2 Installation Exits* for information on installation exit routine coding and implementation.

Creating a JESNEWS Data Set

The JESNEWS data set is EBCDIC text (news) to be printed by the JES2 print processor immediately following the JES2 information at the beginning of the output separator page. Use the JESNEWS data set to distribute information of general interest to users of a computing installation. For example, you can inform your customers of updated libraries or scheduled outages. This news can appear on the separator page itself if the number of news lines plus the number of lines on the print separator fits on a single page.

The JESNEWS data set is represented in the system by a started task (STC) with the job name \$JESNEWS. The news is shared among all processors in a multi-access spool configuration; when one processor updates the news, all processors automatically pick up the updated news.

The JESNEWS data set is created by a user-defined job through the use of a SYSOUT DD statement. The user-defined job's SYSOUT DD statement must specify an external writer name of JESNEWS. When RACF is active, the userid on the job creating the JESNEWS data set must have sufficient RACF authority to update the JESNEWS data set. If RACF is not active, JES2 issues message \$HASP360 to ask the operator if the user-defined job has authority to create or change the JESNEWS data set. See "Part 7. Providing Security for JES2" on page 341 for additional information on protecting JESNEWS.

Any direct access file with a record length (LRECL) and block size (BLKSIZE) that is acceptable to IEBGENER as SYSUT1 input can be used to create the JESNEWS data set.

Notes:

1. You must use ANSI-control characters for JESNEWS to print properly on a PSF-controlled printer.
2. If RACF and the SECLABEL class are active, RACF assigns the SECLABEL of the last job that updated JESNEWS to the JESNEWS profile. This could cause jobs with lower SECLABELs than the updating job to miss important information and RACF will record security violations for jobs accessing JESNEWS that did not previously occur.

For example, to create a JESNEWS data set, code:

```
//UP$NEWS JOB ...
//JESNEWS EXEC PGM=IEBGENER
//SYSIN DD DUMMY
//SYSPRINT DD DUMMY
//SYSUT2 DD SYSOUT=(A,JESNEWS),DCB=(LRECL=80,
// RECFM=FBA,BLKSIZE=80)
//SYSUT1 DD *
        NEWS
        NEWS
        .
        .
        .
        NEWS
JES2 is up and works fine.
The computer center will be closed on Sunday, the 23rd.
/*
```

When defining the JESNEWS data set on the SYSOUT DD statement, all other DD parameters (except SYSOUT CLASS, DCB, HOLD, and FREE) are ignored. The class name subparameter of the SYSOUT parameter is used only to determine dummy and hold status. Any /*OUTPUT and JCL statements associated with the created JESNEWS data set are ignored. If JESNEWS is defined as a non-held data set, the news will be updated at unallocation time. If you define JESNEWS as a held data set, JES2 will update the news when the data set is released, either by the operator (through either a \$O J or a \$T OJ command) or by a time-sharing request. JES2 writes a message (\$HASP316) to the console whenever a JESNEWS data set is replaced or deleted.

Both forms of carriage control, ANSI or machine code, are accepted (see the RECFM subparameter of DCB in *z/OS MVS JCL Reference*). If the JESNEWS data set exists, the page eject (skip-to-channel 1) operation following the printing of header pages is suppressed so that the installation news can be printed on the separator page. If you want the news to start on its own page, then the appropriate carriage control character should be used.

The JESNEWS is deleted by creating a null data set. This is accomplished by opening and then closing a JESNEWS data set that has no data, or by not opening the JESNEWS data set after it has been allocated. The JESNEWS data set is also deleted by a cold start. There are no restrictions as to when the JESNEWS data set can be changed.

To delete a JESNEWS data set by opening a null data set code:

```
//DEL$NEWS JOB ...
// EXEC PGM=IEBGENER
//SYSPRINT DD DUMMY
//SYSIN DD DUMMY
//SYSUT1 DD DUMMY
//SYSUT2 DD SYSOUT=(A,JESNEWS)
```

To delete a JESNEWS data set by not opening the data set code:

```
//DEL$NEWS JOB ...
//DELNEWS EXEC PGM=IEFBR14
//JESNEWS DD SYSOUT=(A,JESNEWS)
/*
```

Additionally, if you need to suppress the printing of the JESNEWS data set, use Exit 1 or Exit 23. See *z/OS JES2 Installation Exits* for information about these exits.

JES2 System Data Sets

The job log is a collection of data sets that include the user's console messages and replies to WTORs issued during job processing. The job log can appear in the job output on the page following the job's separator page. The job log is grouped into a single output group and only printed once. Installations can choose to print or suppress the job log by using the JES2 JOBCLASS initialization statement or by using JCL.

The system ID and system NODE found in the title line of the JES2 job log are the JES2 member name and NODE name of whichever phase of JES2 processing first puts messages into the job log.

To provide an indication when a particular message was logged for jobs that run multiple days, JES2 provides day/date messages in the JES2 JOBLLOG. The time stamp on the first message matches the time that the first data record (PUT) was processed. The time stamp on all subsequent day/date messages is always midnight (00.00.00). Refer to Figure 21 on page 140 to illustrate the following example: If a job is submitted on day 1 (27 MAR 1995), issues no messages for the next three days (28, 29, and 30 March), and ends on day 5 (31 MAR 1995), the JOBLLOG contains two dates only; the first at the top of the JOBLLOG when the job began and the second prior to the end on day 5 at midnight. There is no entry for a day in which no messages were logged, and therefore, never two consecutive lines with the day/date message.

```

JES2 JOB LOG - SYSTEM A Q T S - N O D E P O K E Y

- MONDAY, 27 MARCH 1995 -
IRR010I  USERID PAULAK  IS ASSIGNED TO THIS JOB.
ICH70001I PAULAK  LAST ACCESS AT 09:13:23 ON WEDNESDAY, MARCH 29, 1995
$HASP373 PAULAKD  STARTED - INIT 12 - CLASS U - SYS AQTS
IEF403I PAULAKD - STARTED - TIME=09.17.56
- =====
-                               REGION          - STEP TIMINGS -          -PAGING COUNTS-
- STEPNAME PROCSTEP PGMNAME      CC      USED      CPU TIME  ELAPSED TIME  EXCP      SERV  PAGE  SWAP
- TSO                IKJEFT01    00      452K    00:00:01.46  00:00:06.48   538      37817    0    0
- FRIDAY, 31 MARCH 1995 -
$HASP395 PAULAKD  ENDED
IEF404I PAULAKD - ENDED - TIME=15.20.02
- =====
- NAME-PAULAK              TOTALS: CPU TIME= 00:00:51.46  ELAPSED TIME= 04:06:06.51  SERVICE UNITS=
- =====
- JES2 JOB STATISTICS -
  27 MAR 1995 JOB EXECUTION DATE
    72 CARDS READ
    7,287 SYSOUT PRINT RECORDS

```

Figure 21. Sample JES2 Job Log

JES2 produces JES2 system data sets for each job according to parameters defined on the JESDS JCL statement or the /*JOBPARM JES2 control statement. These data sets are collectively called the *job log*. These data sets are written by JES2 and accompany user's output; they can also be accessed by the process SYSOUT (PSO) interface through the external writer or using the TSO/E OUTPUT command.

Table 34 shows the names and purposes of these JES2 system data sets.

Table 34. JES2 System Data Sets

Data Set Name	Purpose of dataset
JESJCLIN	Indicates the actual JCL submitted.
JESMSGLG	Indicates any system messages for this job.
JESJCL	Indicates all job control statements in the input stream, that is, all JCL statements and JES2 control statements, plus all procedure statements from any in-stream or cataloged procedure a job step calls, plus all messages about job control statements.
JESYSMSG	Indicates the job's hardcopy log, which contains the JES2 and operator messages about the job's processing: allocation of devices and volumes, execution and termination of job steps and the job, and disposition of data sets.

JES2 does not produce JES2 system data sets for jobs that do not complete execution (that is, jobs that specify TYPRUN on JOB JCL statements, JCL errors, or failure due to an MVS system failure). See *z/OS MVS JCL Reference* for information about using the job log.

For more information on displaying or suppressing a job log, see *z/OS JES2 Initialization and Tuning Reference*.

The JES2 Job Statistics

The JES2 job statistics uses data accumulated while processing JCL statements and SYSIN data to determine the number of input records read, and, while creating SYSOUT, to determine the number of print and punch records. The number of

records reflect the actual records written to the spool and might not necessarily indicate the number of cards, lines, or pages of output; this is also true for the number of SYSOUT spool bytes. For example, specifying multiple copies or using a punch with print commands can result in differences between the number of records in the JES2 job statistics and the number of lines or pages actually printed or cards actually punched.

The following is an example of the JES2 job statistics as they appear in the JES2 JOBLLOG:

```
-----JES2 JOB STATISTICS-----  
  
14 OCT 1992 JOB EXECUTION DATE  
  
8,075 CARDS READ  
  
428 SYSOUT PRINT RECORDS  
  
0 SYSOUT PUNCH RECORDS  
  
82 SYSOUT PAGE RECORDS  
  
36 SYSOUT SPOOL KBYTES  
  
0.52 MINUTES EXECUTION TIME
```

The JES2 Punch Separator Card

JES2 can optionally precede each job's punch output with an identification card. To make the card easy to identify, it has an 11-punch and a 12-punch in all 80 columns. To make the room number and job number easy to read, each digit extends over 6 columns. JES2 converts alphabetic characters into numerical digits as shown in Table 35.

Table 35. Alphabetic Character Conversion to Digits for JES2 Punch Separator Cards

Alphabetic Characters	Numeric Digits
A or J	1
B, K, or S	2
C, L, or T	3
D, M, or U	4
E, N, or V	5
F, O, or W	6
G, P, or X	7
H, Q, or Y	8
I, R, or Z	9

JES2 routes the punch separator card to the stacker designated as the default on each punch device as follows:

- The default for the 2540 punch device is stacker 2. JES2 punches a blank card immediately following the separator card for this device; then JES2 routes this card to stacker 1. JES2 also punches a blank card at the end of each data set and routes them to stacker 1. The blank cards in stacker 1 separate error cards from unselected stacker 2 data sets.

- The default for the 3525 punch device is stacker 1. JES2 punches a blank card at the end of each data set and routes the card to stacker 1. These blank cards separate data sets in stacker 1 from unselected cards.

On either device, JES2 routes any card that has an incorrect carriage control (command control) or incorrect print line to stacker 1.

Output Routing

If allowed by the security product, you can route output to:

- A specific local or remote device
- A remote job entry (RJE) workstation
- A pool of remote job entry (RJE) workstations
- A JES2 node or nodes
- A non-JES2 node or nodes
- Remote terminals attached to a JES2 or non-JES2 node
- A specific destid at this or another node
- A specific userid at this or another node

Routing Data Sets

You can route a specific data set by using the DEST parameter of the DD statement, a specific data set or group of data sets by using the OUTPUT JES2 control statement or the OUTPUT JCL statement, or the entire print/punch output for the job by using the /*ROUTE statement.

JES2 uses the destination specified for a data set on the OUTPUT JES2 control statement, the OUTPUT JCL statement, or the DD JCL statements. However, output data sets routed to a remote workstation using the OUTPUT or DD JCL statements, or the DEST= DD parameter cannot be altered by a remote operator; the job-level default controls access to those data sets. To discover the job-level default, enter the \$D J1-999 operator command. For data sets with no destination specified, JES2 uses the destination on the /*ROUTE statement or the default destination specified on the input devices from which the job was submitted.

The DEST=parameter on the DESTID(jxxxxxxx) initialization statement provides route codes for destinations on this node and other nodes. A complete destination specifies both a second-level destination and first-level destination for SYSOUT. Second-level destinations specify the final destination (LOCAL, Rmmmm, Unnnn, userid) at a node (the first-level destination) specified previously on either a /*ROUTE PRT or a /*ROUTE PUN JES2 control statement, or defaulted as specified below. For more information on how to specify and use destination identifiers (destids), see "Using Destination Identifiers to Route Output" on page 143.

Pooling Remote Devices

By assigning the same destid to a group of remote workstations or a group of devices, you can create a remote pool or device pool. Remote device pooling can identify a particular printer for more than one remote workstations. For more information on pooling remote devices, see Chapter 6: "Remote Job Entry".

Specifying Default Output Routing On Input Devices

You can specify the default print and punch destination on the readers through which the system receives the job, using the following statements:

- RDR(nn) PRTDEST= ,PUNDEST= for local readers.
- R(nnnn).RD(m) PRTDEST= ,PUNDEST= for remote readers.
- For INTRDR(nn) specifying a destination by way of JCL (DEST=).

(If you do not specify the default print and punch destination, the default output routing becomes the destination associated with the input device.)

In the case of an internal reader, the DEST= parameter for the internal reader allocation determines the default print and punch destination. If the DEST= parameter does not specify a destination for the internal reader, the destination for the output is the location that originally submitted the job. For example, you can submit a job on NODEA and route it for execution on NODEB. The output, however, returns to NODEA unless you specified the DEST= parameter as NODEB or some other location.

You can use JCL with either the /*ROUTE statement or the DEST= subparameter in the DD SYSOUT statement to specify a particular device.

Allowing Output Devices to Select Route Codes: You can define output devices, such as printers and punches, so that they can select route codes for themselves and for remote workstations during JES2 initialization. Use the following initialization statements:

- OFF(n).ST for SYSOUT transmitters.
- PRT(nnnn) for local printers.
- PUN(nnnn) for local punches.
- R(nnnn).PR(m) for remote printers.
- R(nnnn).PU(m) for remote punches.

If you specify R on an output device's work selection parameter, the device can select only output with a route code that matches a route code specified on the output device's Routcde= parameter. To specify work selection values for an installation's readers, printers, and punches, see "Variable Work Selection Criteria" on page 116. Most devices specify R in their WS= list. If they do not, JES2 assumes that the device can select output with any route code. JES2 does not allow printers and punches to select output destined to a different node.

Using Destination Identifiers to Route Output

JES2 allows users to specify where output should go by using destination identifiers. These destination identifiers (destids), together with JES2 route codes, allow installations a method of sending output to different nodes, remote workstations, and special local devices.

JES2 destinations are composed of two parts:

- A first-level destination indicating a particular node.
- A second-level destination indicating a remote workstation, special local route code, or userid at that node.

Each node in a JES2 network automatically receives a destination identifier through the NAME= parameter on the NODE initialization statement and the \$T NODE command. If you do not specify a destination identifier for the NAME= parameter, JES2 provides a default value. For example, the NODE(1) NAME= parameter defaults to 'N1' where 'N' is a special prefix indicating this is a node.

Installations can specify a symbolic name as a destid through the DESTID initialization statement subscript (jxxxxxx). The DESTID subscript (jxxxxxx) specifies the 1- to 8-character name that installations can use to refer to these JES2 destinations.

The DEST= parameter on the DESTID(jxxxxxx) initialization statement specifies a route code that JES2 uses to send both jobs and SYSOUT from one destination to

another. These route codes can be defined as numbers preceded by a prefix that has special meaning. For example, the prefix 'N' can indicate that the destination identifier represents a particular node. Other prefixes represent a remote workstation ('R', 'RM', or 'RMT') or a special local route code ('U') defined across a number of installations.

Specifying SYSOUT Destination Through JES2 Route Codes: When SYSOUT data sets are created, they are assigned routing information. That routing information can cause the data set to be sent to another node or be processed locally. Local printers are also assigned routings that are used to select data sets to print. Routings that are valid for printer selection are:

- LOCAL or ANYLOCAL
- Remote routing (Rmmmm)
- Special local routing (Unnnn)
- User routing (8-character name with no special meaning).

Using remote routings or special local routings provides better performance because there tends to be less output queued to those routings. But these routings are difficult for end users to remember and cause problems if they need to change. By using the DESTID(jxxxxxxx) initialization statement, an installation can associate a meaningful name with a remote or special local routing that is easy to remember and insulates the end user from changes made to the system configuration.

Figure 22 illustrates how an installation can use the DESTID(jxxxxxxx) initialization statement to associate a meaningful name with a special local routing that insulates end users from changes made to the network configuration. Nodes 1 and 2 use a 3820 printer (PRT1) located at Node 1 to print all SYSOUT. The destid 'TOM' can be specified (DEST=TOM) on either a JCL statement or a JES2 control statement at other nodes to ensure that JES2 routes SYSOUT to the 3820 at NODE 1.

At Node1: DESTID(TOM) DEST=N1.U5
PRT(1) START=YES,SEP=NO,UNIT=0008,R=U5

At Node2: DESTID(TOM) DEST=N1.U5

Figure 22. Using Destids to Route Output to a Printer at Another Node

If end users and application programs are using destids to route SYSOUT and jobs, they will be insulated from configuration changes. As configurations change, installations can change the routing associated with the DESTID(jxxxxxxx) initialization statements to match the new configurations.

For example, an installation wants to move printer 1 to Node 2 or switch the work load that had been sent to Node 1 to another printer at Node 2. The installation can define a printer at Node 2 that selects the same special local route code and change only the first-level destination identifier of DESTID(TOM) from 'N1' to 'N2'. SYSOUT with a destination of 'TOM' is now sent to Node 2, where it is selected by the printer with the same special local routing. Figure 23 on page 145 displays the changed initialization statements.


```

At Node1: DESTID(TOM) DEST=N2.U5

At Node2: DESTID(TOM) DEST=N2.U5
             PRT(1) START=YES,SEP=NO,UNIT=0008,R=U5

```

Figure 23. Destids When Printer Moved to Node 2

Routing Output After a Configuration Change: To ensure that all output that had been created using the old destid of 'U5' does not remain on spool unprocessed, operators should route this output from special local routing 5 to destid 'TOM' through the \$R command:

```
$R ALL,R=U5,D=TOM
```

Specifying SYSOUT Destination Through User Routing: Insulation from configuration changes can also be achieved for different nodes in a network through user routing. Installations at nodes 1, 2, and 3 can logically move a printer from Node 2 to Node 3 without causing Node 1 to make any changes.

For example, consider the following figure. An installation has eliminated printer 1 from NODE2. Work that had printed on printer 1 should be routed to printer 3 at node 3. End users and application programs on nodes 1, 2, and 3 all route SYSOUT to the printer using a destid of 'TOM'. Figure 24 shows the destids before and after the move.

```

BEFORE
At Node1: DESTID(TOM) DEST=N2.TOM

At Node2: DESTID(TOM) DEST=N2.U5
             PRT(1) START=YES,SEP=NO,UNIT=0008,R=U5

At Node3: DESTID(TOM) DEST=N2.TOM

AFTER
At Node1: DESTID(TOM) DEST=N2.TOM

At Node2: DESTID(TOM) DEST=N3.TOM

At Node3: DESTID(TOM) DEST=N3.U3
             PRT(3) START=YES,SEP=NO,UNIT=000A,R=U3

```

Figure 24. Moving Printers without Notifying Other Nodes

Notice in Figure 24, the DESTID(TOM) on node 1 was not changed. Node 1 defined the destination identifier 'TOM' as meaning: Route the SYSOUT to whatever 'TOM' is on node 2. Before the move, 'TOM' on node 2 was the special local routing 'U5'. After the move, 'TOM' on node 2 was updated to route the SYSOUT to whatever 'TOM' is on node 3. This technique of routing a destid to user routings at other nodes allows configuration changes at one site without the need to update all other nodes simultaneously.

The use of symbolic route codes allows an installation to associate a meaningful name(s) with a remote or special local routing. Care must be used when creating a DESTID with a symbolic DEST= parameter if that parameter is also used as a DESTID subscript or node name in the same initialization stream. JES2 enforces an order-dependency of destination definitions:

1. Destinations defined within the same initialization stream.
JES2 will allow the use of a symbolic DEST= parameter if it is:

- Never defined as a DESTID subscript or node name in the same initialization stream. In this case, the symbolic DEST= parameter is treated as if it were a userid.
- Used as a DESTID subscript or node name in an initialization statement that occurs earlier in the initialization stream. In this case, the destination will resolve to that defined for the first initialization statement. This 'look-up' will continue until a non-user route code is encountered.

If a DESTID is created with a symbolic DEST= parameter, and that parameter is used as a DESTID subscript or node name later in the same initialization stream, JES2 will treat it as an error condition. Message \$HASP512 will be issued to indicate an error for the first DESTID statement.

2. Destinations defined using the JES2 \$ADD command.

JES2 will resolve destinations defined using a \$ADD DESTID(jxxxxxxx), DEST=symbolic_parameter in a method similar to that described above for DESTID statements that appear in initialization streams. The following rules apply if the symbolic DEST= parameter is:

- Used as a DESTID subscript or a node name in the initialization deck, the destination will resolve to that defined by the initialization statement.
- Used as a DESTID subscript in a previous \$ADD DESTID(jxxxxxxx) command, the destination will resolve to that defined by that (previous) command.
- Not already defined as a destination it will always resolve to the DEST= parameter value, regardless of whether or not it is defined in a subsequent \$ADD command.

Table 36 shows how an installation can use symbolic route codes to allow users to route SYSOUT to one node using several different destination names.

SYSOUT can be routed to node N10 using the destination names defined in the initialization stream, 'NYC' and 'BIGAPPLE'. SYSOUT can also be routed to N10 using destination name NEWYORK after the first \$ADD command is issued. Because NODE10 is defined as N10 in the third \$ADD command, the fourth \$ADD command can use route code NODE10 to define destination BIGCITY, which again resolves to node N10.

Table 36. How JES2 Resolves Destinations with Symbolic Route Codes

Initialization Statements/JES2 Commands	JCL Destination	Resolved Destination
DESTID(BIGAPPLE) DEST=N10 DESTID(NYC) DEST=BIGAPPLE N(10) NAME=RUDYJ	BIGAPPLE	N10
	NYC	N10
\$ADD DESTID(NEWYORK), DEST=BIGAPPLE	NEWYORK	N10
\$ADD DESTID(NYCITY), DEST=N10	NYCITY	NODE10*
\$ADD DESTID(NODE10), DEST=N10 \$ADD DESTID(BIGCITY), DEST=NODE10	NYCITY	NODE10*
	BIGCITY	N10
* Destination NYCITY will always resolve to NODE10, because NODE10 was not yet defined.		

Table 37 illustrates the error case described in the ‘initialization statement’ section above. Symbolic DEST= parameter BIGAPPLE is used in the first initialization statement. However, DESTID BIGAPPLE is created in a subsequent initialization statement. JES2 will issue message HASP512 to indicate that DESTID NYC is in error.

Table 37. How JES2 Resolves Destinations with Symbolic Route Codes

Initialization Statements/JES2 Commands	JCL Destination	Resolved Destination
DESTID(NYC) DEST=BIGAPPLE	NYC	LOCAL
DESTID(BIGAPPLE) DEST=N10	BIGAPPLE	N10

How JES2 Resolves Destinations from Node to Node

A destination can be specified to a JES2 system through a variety of methods, including the following:

- JES2 commands
- The DEST= parameter on a JCL OUTPUT statement
- An SDSF over-type field
- The PRT= or PUN= parameter on a JES2 control ROUTE statement.

There are different types of JES2 processing for destinations received at the:

- Origin node
- Destination node

Origin Node Processing

At the first node (the origin node) to receive a JES2 destination through one of the methods cited above, destinations can be translated to new values when the specified second-level destination equals the subscript on a DESTID(jxxxxxxx) initialization statement. Two types of change can occur:

Case 1: The specified first-level destination equals the first-level destination on the DESTID(jxxxxxxx) initialization statement.

Action: JES2 replaces the specified second-level destination with the second-level destination on the DEST= parameter on the DESTID(jxxxxxxx) initialization statement.

Case 2: The DEST= parameter does not have a first-level destination.

Action: JES2 replaces the specified second-level destination with the second-level destination on the DEST= parameter of the DESTID(jxxxxxxx) initialization statement.

Note: If the DEST= parameter specifies a DESTID previously created in the initialization stream, then the DEST parameters of the first DESTID(jxxxxxxx) initialization statement will apply.

Destination Node Processing

At the node where a JES2 destination is received, that destination can be translated to new values when the second-level destination received from the network job header equals the subscript on a DESTID(jxxxxxxx) initialization statement.

Action: JES2 replaces the entire destination with the value of that DEST= parameter.

Note: The data could be routed to another node.

Examples of JES2 Routing SYSOUT Destinations: The following examples, read from left to right, display how JES2 receives data, interprets that data, and resolves the destination as it travels from node to node. Throughout these examples, the following parameters on the DESTDEF initialization statement use their default values.

Ndest=
RIRMIRMTdest=
Udest=

Example 1:

Table 38. How JES2 Resolves Destinations -- Example 1

1 Destination Specified at NODE 1	2 DESTID Specified at NODE 1	3 Destination Sent (NJE Header)	4 DESTID Specified at NODE 2	5 Destination Resolved
NODE2.TOM	DESTID(TOM) DEST=NODE2.FRED	NODE2 FRED	DESTID(FRED) DEST=BOB	NODE2.BOB

1 The destination specified on a //OUTPUT JCL statement, NODE2.TOM, means: Send this SYSOUT to destination TOM at Node 2.

2 JES2 determines whether Node 1 has a definition for destination TOM. It finds a DESTID(TOM) initialization statement. Comparing the first-level destinations and finding that they match (that is, NODE2 on the OUTPUT JCL statement and the DEST= parameter specifies NODE2), JES2 uses the second-level destination (FRED).

3 JES2 puts the destination of FRED at NODE2 into the NJE header and sends the SYSOUT to Node 2.

4 At Node 2, JES2 takes the incoming destination of FRED and checks to see if it is defined as a destination identifier. There is a DESTID(jxxxxxx) initialization statement definition for FRED. Its DEST= parameter specifies only a second-level identifier of BOB. Therefore, the first-level identifier is assumed to be Node 2.

5 The resolved destination is BOB at Node 2.

Example 2:

Table 39. How JES2 Resolves Destinations -- Example 2

1 Destination Specified at NODE 1	2 DESTID Specified at NODE 1	3 Destination Sent (NJE Header)	4 DESTID Specified at NODE 2	5 Destination Resolved
NODE2.JACK	DESTID(JACK) DEST=NODE3.R5	NODE2 JACK	DESTID(JACK) DEST=NODE3.R5	NODE3.R5

1 The destination specified on an SDSF over-type field, NODE.JACK, means: Send this SYSOUT data set to destination JACK at Node 2.

2 JES2 determines whether Node 1 has a definition for destination JACK. It finds a DESTID(JACK) initialization statement definition. Comparing the first-level identifiers, JES2 finds no match (that is, NODE2 specified on the SDSF over-type and the DEST= parameter specifies NODE3). JES2 ignores the DEST= specification.

3 JES2 puts the destination of JACK at NODE2 into the NJE header and sends the SYSOUT to Node 2.

4 At Node 2, JES2 takes the incoming destination of JACK and determines if it is defined as a destination identifier. There is a DESTID(JACK) initialization statement. Its DEST= parameter specifies NODE3.R5. Because this is the specification defined at Node 2 (the destination node), JES2 uses it.

5 The resolved destination is R5 (remote workstation 5) at Node 3.

Example 3:

Table 40. How JES2 Resolves Destinations -- Example 3

1 Destination Specified at NODE 1	2 DESTID Specified at NODE 1	3 Destination Sent (NJE Header)	4 DESTID Specified at NODE 2	5 Destination Resolved
NODE2.BILL	DESTID(BILL) DEST=NODE2.JOHN	NODE2 JOHN	DESTID(JOHN) DEST=NODE3.U5	NODE3.U5

1 The destination specified on a /*ROUTE PRT JES2 control statement, NODE2.BILL, means: Send this SYSOUT data set to destination BILL at Node 2.

2 JES2 determines whether Node 1 has a definition for destination BILL. It finds a DESTID(BILL) initialization statement definition. Comparing the first-level identifiers and finding that they match (NODE2 specified on the /*ROUTE statement and the DEST= parameter specifies NODE2), JES2 uses the second-level destination (JOHN).

3 JES2 puts the destination of JOHN at NODE2 into the NJE header and sends the SYSOUT to Node 2.

4 At Node 2, JES2 takes the incoming destination of JOHN and determines if it is defined as a destination identifier. There is a DESTID(JOHN) initialization statement. Its DEST= parameter specifies NODE3.U5. Because this is the specification defined at Node 2 (the destination node), JES2 uses it.

5 The resolved destination is U5 (special local routing 5) at Node 3.

Example 4:

Table 41. How JES2 Resolves Destinations -- Example 4

1 Destination Specified at NODE 1	2 DESTID Specified at NODE 1	3 Destination Sent (NJE Header)	4 DESTID Specified at NODE 2	5 Destination Resolved
NODE2.SCOTT	DESTID(SCOTT) DEST=R5	NODE2 R5	N/A	NODE2.R5

1 The destination specified on a \$TO J5,ALL,D= JES2 command, NODE2.SCOTT, means: Send this SYSOUT data set to destination SCOTT at Node 2.

2 JES2 determines whether Node 1 has a definition for destination SCOTT. It finds a DESTID(SCOTT) initialization statement definition. JES2 cannot compare first-level destinations because the DEST= parameter provides only a symbolic second-level destination. Therefore, JES2 uses the first-level destination from the \$T O command and combines it with the second-level destination on the DEST= parameter from the DESTID(jxxxxxx) initialization statement.

- 3** JES2 puts the destination of R5 at NODE2 into the NJE header and sends the SYSOUT to Node 2.
- 4** At Node 2, because the incoming destination is an explicit destination (referring to a specific route code) as opposed to a symbolic destination, JES2 uses it.
- 5** The resolved destination is R5 (remote workstation 5) at Node 2.

Example 5:

Table 42. How JES2 Resolves Destinations -- Example 5

1 Destination Specified at NODE 1	2 DESTID Specified at NODE 1	3 Destination Sent (NJE Header)	4 DESTID Specified at NODE 2	5 Destination Resolved
NODE2.ROY	DESTID(ROY) DEST=FRED	Node2 FRED	DESTID(FRED) DEST=U2	NODE2.U2

- 1** The destination specified on a //OUTPUT JCL statement, NODE2.ROY, means: Send this SYSOUT data set to destination ROY at Node 2.
- 2** JES2 determines whether Node 1 has a definition for destination ROY. It finds a DESTID(ROY) initialization statement definition. JES2 cannot compare first-level destinations because the DEST= parameter provides only a symbolic second-level destination. Therefore, JES2 uses the first-level destination from the OUTPUT JCL statement and combines it with the second-level destination on the DEST= parameter from the DESTID(jxxxxxx) initialization statement.
- 3** JES2 puts the destination of FRED at NODE2 into the NJE header and sends the SYSOUT to Node 2.
- 4** At Node 2, JES2 takes the incoming destination of FRED and determines if it is defined as a destination identifier. There is a DESTID(FRED) initialization statement. Its DEST= parameter specifies the explicit destination U2. Because this is the specification defined at Node 2 (the destination node), JES2 uses it.
- 5** The resolved destination is U2 (special local routing 2) at Node 2.

Routing Output to Devices at Another Node

There are two ways to route output to devices at another node:

1. By defining both the target node and the specific destination on that node.
(‘N2.R5’ signifies remote 5 at node 2.)

Remember that if you define a destination node that is different from the node where the output was created, JES2 processing will interpret destinations (for both jobs and SYSOUT) at both the creation and destination nodes.

2. By using a DESTID defined on that node.

‘BOST1.R2’ signifies a remote workstation ‘R2’ at node BOST1
Node 2 for the example in
Figure 25 on page 151.

An installation could change BOST1.R2’s routing on the DEST= parameter to a different route code without affecting other nodes and user applications in the network.

To illustrate this process, refer to the initialization parameters defined in Figure 25.

<p>WASH1</p> <p>NODE(1) NAME=WASH1 NODE(2) NAME=BOST1 DESTID(FIRST) DEST=BOST1.R1 DESTID(SECOND) DEST=BOST1.SECOND DESTID(THIRD) DEST=BOST1.THIRD</p> <p>DET1</p> <p>NODE(1) NAME=WASH1 NODE(2) NAME=BOST1 NODE(3) NAME=DET1 DESTID(SECOND) DEST=BOST1.R2 DESTID(THIRD) DEST=DET1.R1</p>	<p>BOST1</p> <p>NODE(1) NAME=WASH1 NODE(2) NAME=BOST1 DESTID(SECOND) DEST=BOST1.R2 DESTID(THIRD) DEST=DET1.THIRD</p>
--	---

Figure 25. Sample JES2 DESTID(jxxxxxxx) Initialization Values on Three Nodes

Output at WASH1 routed to destination FIRST is sent to Remote 1 at BOST1. The destination is resolved at BOST1. Because a BOST1 remote number is defined in the initialization statement shown for WASH1, the destid FIRST need not be defined at BOST1.

Output at WASH1 routed to destination SECOND is sent to BOST1 and the output sent to remote 2. The destination SECOND must be defined on both nodes. WASH1 does not need to know which remote on BOST1 represents SECOND. If SECOND was not defined at BOST1, JES2 would send output to userid SECOND. If there were no such user on the system, the output would remain on the userid queue at BOST1 until an operator changed its destination or the data set was purged.

Output at WASH1 routed to destination THIRD is sent to BOST1, where it is rerouted to THIRD at DET1. Finally, DET1 receives the output and routes the job to remote workstation 1 at DET1. If no destid had been defined as DESTID(THIRD), JES2 would have routed the data to userid 'THIRD' at DET1.

Avoiding Endless Looping in a Network

When planning a network, ensure that all NODE(nnnn) and DESTID(jxxxxxxx) initialization statements have been defined to prevent endless looping throughout the network. For example, in Figure 26, the output destined for node 2 is routed back and forth in a loop because node 1 assumes that DEST is userid NY6 at node 2 and node 2 assumes that DEST is userid NY5 at node 1.

All nodes in a network need to define JES2 destids using the same conventions so that each system programmer knows what devices, remote workstations, and userids exist at each node.

<p>NODE 1</p> <p>-----</p> <p>DESTID(NY5) DEST=N2.USER</p>	<p>NODE 2</p> <p>-----</p> <p>DESTID(NY6) DEST=N1.USER</p>
--	--

Figure 26. JES2 DESTID(jxxxxxxx) Initialization Values that Loop

Specifying TSO/E Userids on a JES2 System

In order for a userid to receive mail or notification messages from a JES2 subsystem, **never** define userids of the following forms as TSO/E userids:

- ANYLOCALILOCAL
- Any destid name defined on a DESTID(jxxxxxxx) initialization statement

- Any destid name added through a \$ADD DESTID(jxxxxxxx) operator command.
- Any name specified on the NAME= parameter of a NODE(nnnn) initialization statement.
- Any name specified on the NAME= parameter of a \$T NODE(nnnn) operator command.

IBM recommends that installations avoid confusion when routing SYSOUT from one destination to another by not specifying the following forms as userids on a JES2 system:

- Nnnnn
- Rmmmm
- RMmmmm
- RMTmmmm
- NnnnnRmmmm
- Unnnn

An installation using these userids might experience unexpected results. For example, output intended for userid R001 is instead routed to remote 1, even if that remote has not been defined on the system.

Installations that find it necessary to define TSO/E userids beginning with the prefixes 'N', 'R', 'RM', 'RMT' and 'U' can do so by specifying USER on the following parameters of the DESTDEF initialization statement:

- Ndest=
- Rdest=
- RMdest=
- RMTdest=
- Udest=

Installations can also control the number (1-32767) of nodes in a network through the NODENUM= parameter on the NJEDEF statement. For example, if NODENUM=7, JES2 would resolve the route code N17 as a userid at its destination.

Additionally, the LOCALNUM= parameter of the DESTDEF initialization statement defines the maximum number that JES2 identifies as a special local route code. In an installation that defines this parameter, JES2 presumes that any number exceeding the LOCALNUM= value is a userid. For example if LOCALNUM=29, JES2 would resolve the route code U321 as a userid at its destination.

The prefixes R, RM, and RMT can precede a number in the range from 0 to 32767. JES2 provides no means of controlling this range.

Altering Destination Processing Through DESTDEF

JES2 destination processing recognizes certain destination prefixes as having a special meaning. This can cause problems if an installation is using those special prefixes as TSO/E userids: notify messages and netmail files might not reach the intended users. Installations can use options on the DESTDEF initialization statement to prevent these problems. These options alter which prefixes JES2 destination processing recognizes and which it does not.

These are the options on the DESTDEF statement that an installation uses to control which prefixes JES2 recognizes:

Ndest	Nodal routing Nnnnn and NnnnnRmmmm
Rdest	Remote routing Rmmmm and NnnnnRmmmm

RMdest	Remote routing RMmmmm
RMTdest	Remote routing RMTmmmm
Udest	Special local routing Unnnn

When any of these options are set to 'USER', JES2 no longer recognizes any special meaning for the corresponding destinations. This applies to JCL, JES2 control statements (JECL), commands, and dynamic allocation processing. For initialization statement processing, JES2 ignores the meaning of these prefixes for all destination identifiers that appear **after** the DESTDEF statement in the initialization stream unless performing a hot start. If this is a hot start, the values from when JES2 was last active apply to the entire initialization deck.

To avoid different interpretations of destinations on a hot start, the DESTDEF statement should appear early in the initialization stream and before any references to destinations.

The DEST= parameter on the DESTID(jxxxxxx) initialization statement and the \$T DESTID and \$ADD DESTID operator commands are the only places where DESTDEF options never apply. This allows for the creation of destids that route output to a remote even when DESTDEF RDEST=USER.

To illustrate how the DESTDEF initialization statements can be used to enforce particular policies at an installation, consider the following two examples, in which both RDEST=User and SHOWUSER=WITHlocal.

The \$T O command routes all the SYSOUT from job 4 to userid 'R0007'. This installation can require all JCL and JES2 control statements submitting jobs to specify all userids with the single-letter prefix 'R', while still using 'RM' (RMDEST=User) and 'RMT' (RMTDEST=User) to specify remote workstations.

In response to the operator command:

```
$TOJ4,ALL,D=R0007
```

JES2 displays:

```
$HASP686 OUTPUT(IRRDP TAB) OUTGRP=2.1.1,BURST=NO,FCB=****,
$HASP686 FLASH=****,FORMS=STD,HOLD=(NONE),
$HASP686 HOLDRC=,OUTDISP=HOLD,PAGES=,
$HASP686 PRIORITY=144,PRMODE=LINE,QUEUE=A,
$HASP686 RECORDS=(4 OF 4),ROUTECD=LOCAL.R0007,
$HASP686 SECLABEL=,TSOAVAIL=YES,UCS=****,
$HASP686 USERID=+++++++,WRITER=
```

In this example, the route code 'LOCAL.R0007' indicates a userid of R0007 at the local node.

This installation can alter the meaning of 'R0007' by dynamically adding a destid through the following command from the operator console:

```
$ADD DESTID(R0007),DEST=R7
```

JES2 displays:

```
$HASP822 DESTID(R0007) DEST=R7,STATUS=DESTID,PRIMARY=NO
```

Now, if an operator enters the command:

```
$TOJ5,ALL,D=R0007
```

JES2 displays:

```

$HASP686 OUTPUT(IRRDP TAB) OUTGRP=2.1.1,BURST=NO,FCB=****,
$HASP686 FLASH=****,FORMS=STD,HOLD=(NONE),
$HASP686 HOLDRC=,OUTDISP=HOLD,PAGES=,
$HASP686 PRIORITY=144,PRMODE=LINE,QUEUE=A,
$HASP686 RECORDS=(4 OF 4),ROUTECD=R0007,
$HASP686 SECLABEL=,TSOAVAIL=YES,UCS=****,
$HASP686 USERID=+++++++,WRITER=

```

In this example, the route code 'R0007' indicates the destid R0007 rather than a user destination.

Preparing Installations to Alter Destination Processing

Before changing how JES2 interprets destinations, installations should review their JCL and automated commands to ensure that they are not using the prefixes being affected. For example, before changing Ndest to 'USER', ensure that there are no JCL references to N123, N0123, N000123.

Destids can be used to support cases where it is not practical to change JCL statements. However, the subscript on the DESTID(jxxxxxxx) initialization statement must match the DEST= parameter specification on the JCL statement exactly. For example, an installation with the following initialization statement can route data to node 1 using OUTPUT JCL statements that specify DEST=N1.

```
DESTID(N0000001)
```

To route the data to Node 2, you must specify DESTDEF Ndest=User on a warm start, add the following DESTID,

```
DESTID(N1) DEST=N2
```

and add DEST=N2 to the DESTID(N0000001) initialization statement. If you change any DESTDEF initialization statement parameters to specify User, the processing of explicit destids can be altered. Use the DESTDEF initialization statement to alter destination processing only after carefully preparing the initialization stream definitions and JCL statements carefully. For more information on how to prepare an installation for such a change, see both "Specifying TSO/E Userids on a JES2 System" on page 151 and "Altering Destination Processing Through DESTDEF" on page 152.

An installation can specify whether JES2 displays a destid or an explicit route code for jobs and SYSOUT through the PRIMARY= parameter on both the DESTID(jxxxxxxx) initialization statement and the \$ADD DESTID operator command. For example, by specifying 'DESTID(NYWK),DEST=U2,PRIMARY=YES', an installation ensures that the destid 'NYWK' is displayed instead of the explicit special local route code of 'U2'.

Use of PRIMARY=YES can aid both operators and system programmers in tracking jobs and SYSOUT across a network, as illustrated in Figure 27 on page 155. An installation specifies that destids beginning with the 'RMT' prefix should be processed as userids (RMTdest=USER), then creates the following destids in its initialization stream.

```

DESTDEF      RMTDEST=User,SHOWUSER=WITHlocal
DESTID(RMT6) DEST=R6,PRIMARY=YES
DESTID(DR1)  DEST=R1,PRIMARY=NO
DESTID(DR2A) DEST=R2,PRIMARY=NO
DESTID(DR2B) DEST=R2,PRIMARY=NO
DESTID(DR3A) DEST=R3,PRIMARY=YES
DESTID(DR3B) DEST=R3,PRIMARY=NO
DESTID(DR4A) DEST=R4,PRIMARY=YES
DESTID(DR4B) DEST=R4,PRIMARY=YES
DESTID(DR5)  DEST=N1.R2,PRIMARY=NO
:
:
NJDEF      OWNNO=1

```

Figure 27. DESTID(jxxxxxx) and DESTDEF Initialization Stream Definitions

In Table 43, you can see how these destinations are resolved.

Table 43. How JES2 Resolves Destinations from DESTDEF Initialization Statements

Destid Routing	Console Display	Reason
DR1	DR1	Displays the destid because no other destids specify this routing.
DR2A	R2	Displays explicit destination because neither destid with this routing specified PRIMARY=YES.
DR3A	DR3A	Displays the destid because PRIMARY=YES.
DR3B	DR3A	Displays alternate destid because DR3A shows PRIMARY=YES.
DR4A	DR4A	Displays the destid because PRIMARY=YES.
DR4B	DR4A	Displays alternate destid because both show PRIMARY=YES. and DR4A is first alphabetically. in the initialization stream.
DR5	R2	Displays explicit destination because PRIMARY=NO.
R5	R5	Displays explicit remote workstation routing.
RM5	R5	Displays explicit remote workstation routing.
RMT5	LOCAL.RMT5	Displays user destination because RMTdest=User.
RMT6	RMT6	Displays destid because PRIMARY=YES. and RMTdest=User.

The PRIMARY= parameter on the DESTID(jxxxxxx) initialization statement allows an installation to specify how JES2 resolves multiple destid displays. As Table 43 shows, specifying PRIMARY=YES allows an installation to specify which destid appears in displays when two statements specify the same DEST= routing. For example, destid 'DR3B' will never display on the console because destid 'DR3A' is routed to remote workstation 3 too, and it specifies PRIMARY=YES.

Because the PRIMARY= parameter defaults to NO, you must remember to specify which destid takes precedence when defining two or more with the same DEST= route code.

By specifying SHOWUSER=WITHlocal on the DESTDEF initialization statement, this installation provides a level of clarification in the RMT5 destid routing that displays the first-level identifier 'LOCAL' in front of the userid 'RMT5.'

Routing to Multiple Destids

If there are multiple destids that can be used for a particular routing, one of the destids should be defined as PRIMARY=YES. Failure to do so causes output destined to that routing to display in explicit format, such as Nn, Rm, NnRm, or Un. SDSF displays the routing in this explicit format and attempts to use this format in commands. This explicit routing does not work as expected if one of the DESTDEF initialization statement options is set to 'User'.

For example, in Figure 28, all three destids would match a piece of output routed to special local 5 at the local node (node 1). If you specify the \$DO J command to list the job output for these destids, the console displays a routing of D=U5. However, with Udest=User (and no other destid), using a destination of 'U5' would not result in the same routing as when using a destination of 'DAVE'. If installations define either DESTID(DAVE) or DESTID(MIKE) as PRIMARY=YES, output routed to special local 5 displays with a destination that can be used to route other output to the same place.

```
DESTID(DAVE) DEST=N1.U5
DESTID(MIKE) DEST=N1.U5
DESTID(TOM)  DEST=U5
```

Figure 28. Multiple Destids that Match Output Routed to Special Local 5

For an example of how installations can route jobs and SYSOUT data sets through remote workstation devices, see "Routing to RJE Devices When Rdest=User".

Routing to RJE Devices When Rdest=User

An installation with RJE devices that needs to set Rdest=User must ensure that SYSOUT can still be routed to the RJE device. By default, RJE devices are set up so that SYSOUT from jobs submitted from the RJE device is routed back to the RJE workstation. But if a job submitted on remote 5 is routed to another node to execute, when the SYSOUT returns, it will be routed to destination 'R5'. With Rdest=User, 'R5' will not be interpreted as remote 5 but rather as user routing 'R5'. The remote printer will be unable to print the SYSOUT. To prevent this problem, create a DESTID(Rm) DEST=NxRm where 'x' is the local node number (NJEDEF OWNNODE=) and 'm' is the remote number.

When an RJE device signs on, JES2 attempts to interpret the workstation name sent from the remote while honoring the value specified on the DESTDEF initialization statement. First, JES2 searches the destids for a match to determine the actual remote number. If there is no match, JES2 ignores the values set on DESTDEF (assuming that Ndest=, RIRMIRMTdest=, and Udest= have all been set to USER) while interpreting the workstation name. This would allow a remote to sign on using RMT5, even if RMTdest=USER and there is no DESTID(jxxxxxxx) initialization statement with a subscript of RMT5. If a remote tries to sign on as RMT5 and there is a DESTID(jxxxxxxx) initialization statement with a subscript of 'RMT5' with a DEST= that does not specify a remote on the local node, then the sign on attempt will fail.

Reducing Printing Costs Through Remote Pooling: Remote pooling allows the printers on multiple remote workstations to print the output of any remote in the pool. For more information about pooling remote workstations, see "Pooling RJE Workstations" on page 338. JES2 changes any destination that specifies a specific remote workstation in the pool to the routing of the pool. This change occurs when

JES2 interprets a destination starting with 'R', 'RM', or 'RMT'. If Rdest, RMdest, or RMTdest is set to 'USER', then remote pooling does not occur (even if there is a DESTID(R5)).

Even so, much of the function of remote pooling can be achieved by using destids. For example, in Figure 29, remotes 5, 6, and 9 are pooled. The destids will ensure that SYSOUT routed to R5, R6, or R9 will receive a routing of remote 5.

```
DESTDEF RUSER=USER
```

```
RMT(5) ROUTECDE=5          /* Define the remotes as pooled */
RMT(6) ROUTECDE=5
RMT(9) ROUTECDE=5
```

```
DESTID(R5) DEST=N1R5,PRIMARY=YES /* Define the DESTIDs as routing */
DESTID(R6) DEST=N1R5             /* to the pooled remote */
DESTID(R9) DEST=N1R5
```

Figure 29. Remote Pooling with RDEST=USER

Note: In this example, if a remote tries to sign on with a workstation name of 'R9', that workstation will actually sign on to remote 5. To avoid this problem, sign on with a workstation name of 'REMOTE9' or RMT9 (if RMTdest=REMOTE or there are no destids for RMT9).

External Writers

An external writer can select output from JES2 after JES2 builds the output group from the data sets. Your installation can supply its own writer routines or use the external writer processor supplied by IBM by naming the writer as a subparameter of the SYSOUT= DD keyword. The operator then starts an external writer in a private address space, and the external writer writes the data using QSAM.

For details on the external writer, see "Appendix C. The External Writer" on page 395.

Held Job and Data Set Considerations

You can put a data set into a **hold** condition by explicitly defining it as held or assigning the output to a held SYSOUT class. The operator releases the job using the output (\$O) command or the \$T OJ,NDISP= command; a TSO/E user uses the TSO/E OUTPUT command on a time-sharing terminal.

You can transmit held data sets to an offload data set for future retrieval. If you transmit jobs to other nodes for execution, you must consider when and how the hold status takes effect. JES2 treats jobs placed in hold by the operator differently than jobs placed in hold through JCL or TSO/E commands. The following sections discuss, in further detail, how to define, modify, dispose, and offload held data sets.

Defining Held Data Sets

- JES2 **holds** SYSOUT data sets if:
 - The JCL SYSOUT DD statement contains HOLD=YES regardless of the OUTDisp specification on the OUTCLASS(v) initialization statement.
 - The JCL OUTPUT statement contains OUTDISP=(HOLD,HOLD) or OUTDISP=(KEEP,KEEP), regardless of the OUTDisp specification on the OUTCLASS(v) initialization statement.

- The SYSOUT parameter on the JCL DD statement specifies a class defined as held on the OUTCLASS(v) initialization statement with the OUTDisp parameter.
- JES2 **does not hold** SYSOUT data sets if:
 - The JCL SYSOUT DD statement contains HOLD=NO, regardless of the OUTDisp specification on the OUTCLASS(v) initialization statement.
 - The JCL OUTPUT statement contains OUTDISP=(WRITE,WRITE), regardless of the OUTDisp specification on the OUTCLASS(v) initialization statement.
 - The SYSOUT parameter on the JCL DD statement specifies a class defined as non-held on the OUTCLASS(v) initialization statement with the OUTDisp parameter.

Held Output Processing

Once output is held, JES2 builds a JOE for each job as it does for non-held output. JES2 then retrieves such held output in LIFO order, **not** FIFO order as it does for non-held output.

Modifying and Disposing Held Data Sets

A data set remains in held status until either the TSO/E user releases it on a time-sharing terminal with the TSO/E OUTPUT command or from the SDSF panel, or until the operator modifies the disposition with the \$O (output) command. The operator can either release or cancel held data sets based on time (that is, n days or n hours old) with the \$O command or the \$T OJ command. In this manner, you can easily dispose of held output unnecessarily using spool space and job queue elements (JQEs) for too long a time. If you free up these JQEs regularly, you reduce your installation's JQE needs. As your TSO environment grows in size, it is important to prevent this "wasting" of spool space with unneeded or forgotten held output data sets.

The operator can determine spool usage by issuing the \$D SPL command. This command can also display job utilization of specific spool volumes. (Refer to *z/OS JES2 Commands* for more information on this command.) If the \$D SPL response indicates a particularly high spool usage by a particular job, the operator can take action (cancel, offload, or print) to eliminate that job. Here again, the age parameters on the \$O command are useful.

Type 26 SMF records provide further job spool utilization information. These records include the number of track groups and spool buffers used. If you and the operator monitor spool usage and eliminate unnecessary held data set spool usage, you should be able to more effectively tune the track group size parameter (TGSIZE= on the SPOOLDEF statement), thereby using available spool space more efficiently.

Offloading Held Jobs and Data Sets

An installation can offload held jobs. This is a useful tool you can use to free up spool space. Offload jobs by specifying HOLD=YES and WS=(HOLD/) on the job transmitter (OFF(n).JT). Note that you can also transmit held jobs to the offload data set if you do not add HOLD to the work selection list. JES2 does not change the hold status when you receive the offloaded job. Of course, the operator can purge (or otherwise alter its disposition) it if held for longer than an installation determines to be an appropriate length of time. Or, the operator can release the job with the \$A J operator command.

An installation can also offload held data sets. As with held jobs, JES2 remembers the held attribute across the offload operation. However, for data sets held at the local node, only the job-level work selection criteria on for the OFF(n).ST statement apply. You must explicitly request transmission of held data sets. If you add

OUTDISP=(HOLD,LEAVE) to the OFF(n).ST statement, the offload device can then select held data sets. A request of this type means JES2 will transmit all held data sets for a particular job.

JES2 treats data sets held at the destination node (the target system of the offload operation) as normal SYSOUT subject to the work selection criteria for a SYSOUT transmitter.

Held Data Sets in the NJE Environment

If a job generates a SYSOUT data set and specifies "HOLD=YES" on the DD statement for the data set, the "hold" takes effect on the system which receives the data set. If the job's execution node and the data set's destination node are the same, JES2 performs the hold as soon as the job deallocates the data set. If the job's execution node differs from the job's destination node, JES2 removes the local hold on the data set. This permits JES2 to group the data set into an output group; JES2 then places the output group on the network queue for output groups. The SYSOUT transmitter then selects the data set for transmission.

When JES2 transmits a held data set (possibly at the same time it transmits the job's other data sets), the data set header will reflect the hold status of the data set. When a node receives a SYSOUT data set marked as held, the SYSOUT receiver checks the data set's destination against its own node name. If the data set destination is the receiver's node, the receiver performs normal held data set processing. A TSO/E user can then inspect the data set. Once an operator or TSO/E user releases the held data set, the system no longer holds the data set even though the operator or TSO/E user changed its destination before printing the data set. At each point along the way, you can use the JES2 \$R command to change the data set's destination.

Improving JES2 Processing

If JES2 is slow to process work or respond to operator commands, refer to the description of the following initialization statements (in *z/OS JES2 Initialization and Tuning Reference*) and the other noted sections of this manual for tuning recommendations:

- BERTNUM= parameter on the CKPTSPACE statement
- DEBUG statement
- JOBNUM= parameter on the JOBDEF statement
- JOENUM= parameter on the OUTDEF statement
- RDINUM= parameter on the INTRDR statement
- MEMBER(n) initialization statement
- "Managing Storage in JES2" on page 385
- "Accessing the CKPTn Data Set in a MAS" on page 221

In a multi-access spool environment, also refer to the descriptions of the queue control parameters, HOLD= and DORMANCY= on the MASDEF statement and "MASDEF Queueing Parameters" on page 311 for recommended initial parameter value and tuning information.

Part 3. Spool Volume Configuration, Control, and Performance

Chapter 3. Spool Volume Configuration, Control, and Performance	163
Spool Configuration	163
The SYS1.HASPACE Data Set	163
Naming Conventions	163
Placement	164
Space Allocation	164
Defining Spool Space	165
Spool Allocation	166
Controlling Spool Space	166
Defining the Allocation IOT	167
Defining the Track Group Maps	168
Spool Partitioning	168
Using the FENCE Parameter to Partition Spool Volumes	169
Allocating Tracks and Track Cells	170
Handling Defective Track Groups	170
Dynamic Addition and Deletion of Spool Volumes	171
Status of Spool Volumes	171
Addition of Spool Volumes	172
Deletion of Spool Volumes	173
Performance Considerations and Recommendations	174
Recovering from Spool Volume Failure	174
Spool Performance Considerations	175
Selecting Spool Devices	175
Allocation of Spool Space	176
Track Celling	177
Spool Offload Facility	178
Overview	178
Defining the Offload Facility	179
Selecting Jobs and SYSOUT Through Work Selection	180
Using Uncataloged Data Sets	180
Using Pre-cataloged Data Sets	181
SMF Record Summary: Transmitting and Receiving Jobs and SYSOUT	181
Offloading All Pre-Execution Jobs and SYSOUT	182
Job Disposition	185
Reloading All Pre-Execution Jobs and SYSOUT	186
Offloading Selected Jobs and SYSOUT	188
Reloading Selected Jobs and SYSOUT	190
Using the Spool Offload Facility for Networking	192

Chapter 3. Spool Volume Configuration, Control, and Performance

The spool is the repository for all input jobs and all system output (SYSOUT) that JES2 manages. SYS1.HASPACE (the data set used for storing JES2 maintained data and control blocks) is a JES2-required data set. **Note that the name, SYS1.HASPACE, is the JES2 default name for the required spool data set. If you prefer, this name can be changed by specifying the DSNAME= parameter on the SPOOLDEF initialization statement. However, for convenience of this discussion, the default name will be used.** The specification, management, and placement of this data set affects JES2 performance. This chapter deals with the management of spool data sets, including their specification and important performance considerations.

Spool Configuration

JES2 requires that the SYS1.HASPACE data set be present on direct access volumes. In a multi-access spool configuration, these volumes must be accessible from all member systems.

The following section discusses this data set, the dynamic addition and deletion of JES2 spool data sets, spool space for individual jobs, and the allocation of tracks and track cells on a volume.

“Part 7. Providing Security for JES2” on page 341 discusses how to protect spool data sets with RACF.

The SYS1.HASPACE Data Set

Before JES2 can be initialized, space on a direct access device must be allocated for SYS1.HASPACE. SYS1.HASPACE is the name of one or more data sets used for storing JES2-maintained data and control blocks. These volumes store all job input, job output, JES2 control blocks, and messages queued between shared spool members. The requirements for specifying these data sets follow.

Naming Conventions

Up to 253 volumes can be designated as spool volumes. Spool volumes are identified to JES2 by a volume serial number, the first four or five characters of which are specified by the VOLUME= parameter on the SPOOLDEF statement during JES2 initialization. The first four or five characters specifying the volume serial number of each volume must be identical to the characters specified by the VOLUME= parameter. The fifth and sixth characters can be assigned to designate individual spool volumes and can be any characters that are valid in a volume serial number.

Any volume for which the first four to five characters of the volume serial are a value matching the VOLUME= parameter value on the SPOOLDEF statement is assumed to be a spool volume and should have an allocated SYS1.HASPACE data set. If however, a SYS1.HASPACE data set is not on the volume, message \$HASP414 will be issued and the volume will not be used as a spool volume. The data set name must be SYS1.HASPACE (the default) unless the DSNAME= parameter on the SPOOLDEF statement specifies a different data set name. (Refer to the description of SPOOLDEF in *z/OS JES2 Initialization and Tuning Reference* for further information on this statement, if required.)

Placement

Spool volumes can reside on any combination of direct-access devices which are supported by JES2 and your operating system. That is, you can have a mix of DASD types and models such as a 3390-2, a 3390-3, and several 3380s of various models. Refer to “Appendix A. IBM Devices Supported by JES2 and How to Use Them” on page 379 for these device types. Be certain to consider efficient values for the SPOOLDEF initialization statement parameters BUFSIZE=, TGFSIZE=, and TGNUM= for each specific device type. Optimal values for DASD types and models are presented in Table 78 on page 380 and Table 79 on page 381. JES2 utilizes space from each spool volume, ensuring balanced use of all allocated space. All members of a multi-access spool configuration must have at least one channel path to the devices containing all spool and checkpoint volumes.

IBM recommends that you define the UCBs for spool volumes below 16 megabytes (Mb) in common virtual storage. If you define the UCBs for spool volumes above 16 Mb in common virtual storage, JES2 makes a copy of the UCB below 16 Mb in common virtual storage. Because there is no savings to storage, there is no advantage to defining UCBs for spool volumes above 16 Mb in common virtual storage. For more information on defining UCBs, see *z/OS HCD Planning*.

Through spool-partitioning installation exit routines (which you provide), you can control the specific volumes to which a job is allocated, thus limiting the number of jobs affected by the failure of a single spool volume. Also, use the FENCE parameter on SPOOLDEF initialization statement to limit each job to an installation defined number of SPOOL volumes. Refer to “Spool Partitioning” on page 168 for a discussion of how the SPOOLDEF parameters and Exit 11 and Exit 12 interact to provide your installation with its required spool partitioning needs.

IBM recommends that each spool volume be entirely devoted to JES2. To allocate other frequently-referenced data sets on a spool volume would degrade the efficiency of JES2’s direct-access allocation algorithm.

Note: All JES2 spool data sets are position-dependent once they are allocated. To prevent a spool data set from being moved by a utility program, specify each spool data set as unmovable. Do this by specifying DSORG=PSU on the DCB parameter of each DD statement used to define a spool data set.

Space Allocation

Allocate spool data sets as single-extent data sets; if you allocate additional extents, JES2 uses only the first extent for spool space. Each spool volume must contain a data set named SYS1.HASPACE (unless the DSNAME= parameter on the SPOOLDEF statement specifies another name) in order to be used as a spool volume.

Note: Each spool data set extent must not span the **64K-1** absolute track address on the spool volume. If this spanning should occur during spool allocation, JES2 issues \$HASP443 to have you correct the spool data set allocation “spanning” condition.

The unit of direct-access space allocation for JES2 is the track group. The number of tracks in a track group is obtained by the following formula:

$$\text{Number of tracks / track group} = \frac{\text{TGSIZE on SPOOLDEF stmt}}{\text{buffers per track}}$$

where: TGSIZE=number of buffers in a track group.

Spool space can be allocated by using any valid space specification, but the following considerations should be kept in mind:

- To minimize unused DASD space, you should allocate spool space contiguously, because JES2 only uses the first extent of the spool data set.
- The spool allocation *must* be equal to or greater than the number of tracks in a track group.
- TRK (track) allocations waste less DASD space than CYL (cylinder) allocations, because you can specify the allocation as an integral multiple of a track group.

For further information concerning the JCL SPACE parameter and its syntax, see *z/OS MVS JCL Reference*.

An example of defining spool data sets appears in Figure 30 on page 165.

For multi-access spool configurations, all spool and checkpoint volumes must reside on devices that have at least one channel path to each JES2 system in the multi-access spool environment. If the multi-access spool configuration is a member of an NJE network, NJE commands and messages sent among JES2 systems attached to the shared spool are queued on the spool volume. To calculate the number of track groups normally needed in SYS1.HASPACE for NJE messages, use the following formula:

$$\text{Number of track groups} = \frac{n^2 + n^3}{2}$$

where n is the number of JES2 subsystems attached to the shared spool.

```
//ALLOCATE JOB (...),'PREPARE FOR JES2',MSGLEVEL=1
//ALLOCAT EXEC PGM=IEFBRI4
//*
//SPOOL1 DD DSN=SYS1.HASPACE,UNIT=3390,
//          VOLUME=SER=SPOOL1,DISP=(NEW,KEEP),
//          SPACE=(CYL,884,CONTIG),DCB=(DSORG=PSU)
//*
//SPOOL2 DD DSN=SYS1.HASPACE,UNIT=3390,
//          VOLUME=SER=SPOOL2,DISP=(NEW,KEEP),
//          SPACE=(TRK,13256,CONTIG),DCB=(DSORG=PSU)
/*
```

Figure 30. Example of Defining and Allocating the JES2 SYS1.HASPACE Data Set

Defining Spool Space

Effective use of the JES2-managed spool data sets and subsequent performance of JES2 is based on correct control of the JES2 spool volumes. Spool partitioning, use of track celling, and use of marking bad tracks unavailable are effective spool management techniques.

Spool Allocation

During any of the stages of processing, a job can allocate spool space. The logical record length (LRECL) of the spool allocation is dependent on the device that performs the allocation. The table below shows the maximum LRECL for various devices.

Table 44. Maximum Spool LRECLs

Source	Type	Length
BSC/RJE	Input	80
	Punch*	80
	Print**	32K
SNA/RJE	Input	254
	Output***	32K
Local	Input****	80
	Output	32K
INTRDR	Output	254
NJE	Input	252
	Output	32K
External Writer	Output	32K
TSO/E submits	Input	80

* LRECL is 81 with ASA or machine control.

** Truncated to PRWIDTH.

*** This is LRECL written to spool. Maximum transmitted LRECL is 255.

**** Truncated based on device type.

Controlling Spool Space

Use the SPOOLDEF initialization statement to define your system-wide spooling environment. All parameters on this statement can be displayed by using the \$D SPOOLDEF operator command, and several can also be modified by the \$T SPOOLDEF command. However, if modified, the changed parameter values are not remembered across a JES2 restart, with the exception of the FENCE= parameter specification. (Refer to *z/OS JES2 Commands* for a description of these commands.)


The SPOOLNUM= parameter on the SPOOLDEF statement specifies the number (1 - 253) of JES2 spool volumes available to your complex. Be aware that as you do increase this value above 32, each additional 32 volumes uses 8 times the JOBNUM= specification additional bytes in the JES2 address space. (JOBNUM= is a parameter on the JOBDEF statement.)

Note, spool volumes are allocated in multiples of 32 only. If you specify other than a multiple of 32, the value is rounded up to the next multiple of 32 not to exceed the maximum number of spool volumes (253). Furthermore, a value greater than 253 is automatically decreased to the maximum or 253. Also, be aware that if you specify other than a multiple of 32, JES2 returns the rounded spool number value in response to the \$D SPOOL operator command. For example, if you had previously specified SPOOLNUM=37, JES2 allocates 64 spool volumes and displays 64 in response to the display command.

To specify the size of the track group map (TGM) use the TGSPACE=(MAX=) parameter on the SPOOLDEF statement. JES2 automatically compresses the TGM whenever a spool volume is deleted. This prevents various-length entries from fragmenting TGM space and preventing the use of all available track groups. To keep the operator informed of the current status of track groups on a particular volume, JES2 issues messages \$HASP850 and \$HASP851 when spool volumes are either added or deleted. Use this information to monitor spool volume usage.

Defining the Allocation IOT

The track group allocation entries (TGAEs) and peripheral data definition blocks (PDDBs) are contained in the **allocation IOT** (input/output table). The allocation IOT must fit on a single (4K) page of storage. Refer to Figure 31 for a representation of the allocation IOT while reading the following discussion.



For an Allocation IOT:
Minimum Fixed IOT Size = 288 bytes
Space for PDDBs = BUFSIZE - 288 bytes - (50 x TGAE size)
Number of PDDBs = Space for PDDBs/PDDB size
Number of TGAEs = (remainder from previous divide/TGAE size) + 50

For a Secondary Allocation IOT:
No PDDBs are allocated
Fixed IOT Size = 288 bytes
Number of Trace Group Allocation Entries = (BUFSIZE - 288) / 3

Figure 31. Allocation IOT and Minimum Storage Requirements

Track group allocation entries (TGAE) identify the spool data set on which the track groups reside and the specific track groups within the spool data set. Each TGAE represents a single MTT (the spool allocation unit). The allocation IOT contains a list of all TGAEs allocated to this job and data set. JES2 determines and reserves the amount of space within the allocation IOT for the TGAEs. Space for 50 TGAEs is the minimum reserved. Each TGAE is 3 bytes of information: the first byte contains the extent upon which the track group resides, and the second two bytes identifies the relative track number within the specified extent.

Peripheral data definition blocks (PDDBs) also reside in the allocation IOT. These are required to describe the characteristics of the output data within your system. The number of PDDBs that the allocation IOT can hold is determined by the buffer size you have previously specified with the BUFSIZE parameter on the SPOOLDEF statement. Refer to "Appendix A. IBM Devices Supported by JES2 and How to Use Them" on page 379 for information on and recommended values for specific device types to maximize storage and device utilization.

If a job uses all the TGAEs available within the allocation IOT, JES2 obtains a second spool record, the **secondary allocation IOT**. Except for the IOT data area, the entire secondary allocation IOT contains TGAEs; additional tables are constructed if required. As many secondary allocation IOTs are built as required. These are chained in a push down stack which allows the most recently built IOT to be the most readily accessible (it likely resides in central storage whereas any older IOTs have likely been written to spool). In this manner, JES2 minimizes spool I/O and maximizes performance.

For spin data sets, JES2 reserves the maximum space possible for TGAEs. Only one PDDb is required for spin data sets; this minimizes the possibility of needing a secondary allocation IOT to contain the TGAEs.

Defining the Track Group Maps

Two track group maps are defined to JES2: the master track group map and the “badtrack” map defining those tracks specified as bad by JES2. Use the TGSPACE=(MAX=) parameter on the SPOOLDEF initialization statement to define the number of track groups in your JES2 complex. The maximum value is 9935680; however, the realistic limit is determined by your virtual storage limitations. The rounding factor is 16288.

Note: If the number of track groups you have allocated on each spool volume is not divisible by 8, there will be a discrepancy between the maximum allocatable track groups and the sum of the allocated track groups plus the number of track groups available.

The \$TSPOOLDEF command can be used to modify the TGSPACE=(MAX=) parameter; therefore, you can increase the number of track groups as your current system requires. (Decreasing this value requires a JES2 cold-start.) In this manner, the operator can dynamically add spool volumes with the \$\$ SPOOL command to a maximum of 253 spool volumes. (Refer to “Dynamic Addition and Deletion of Spool Volumes” on page 171 and *z/OS JES2 Commands* for further information on this procedure.)

Spool Partitioning

Spool partitioning is a facility provided within JES2 that permits the explicit identification of spool volumes from which a particular job or job class can allocate track groups. This facility is also referred to as **spool fencing**.

Spool partitioning can be a useful tool to your installation, especially if you anticipate future changes to your spool configuration. Standard JES2 processing allows all jobs to allocate track groups on all available spool volumes; therefore, the deletion of a single volume can involve many jobs. Isolation of long-running jobs, frequently-referenced system jobs, or jobs frequently put into HOLD status for long periods of time to one spool volume (or a small number of spool volumes as specified on SPOOLDEF FENCE=) can greatly benefit future spool volume reconfiguration. Also, if only particular volumes are allowed to allocate track groups to these types of jobs, the status of other volumes can be changed more easily, as required.

The use of spool partitioning is also a tool that is useful for increasing JES2 performance. Isolating frequently-run system jobs on separate volumes increases JES2 performance by permitting access to other volumes containing user-defined work. The manner in which JES2 can define spool partitioning is presented below. The SPOOLDEF initialization statements and two installation exits, Exit 11 and Exit

12, provide methods for accessing and setting the **spool partitioning mask work area**. This allows the installation to assign masks based on, for example, JOBCCLASS, others on JOBNAMEs. You need to determine how your installation wants to compromise between performance and limiting the impact of a failure. For more information on installation exits, see *z/OS JES2 Installation Exits*.

JES2 processes your fencing requirements based on the number of volumes you specify and the system affinity to those volumes.

- **Volume Limits:** JES2 will fence a job to an installation defined number of volumes. In this form of fencing, the job starts with a zero spool partitioning mask work area. As the job allocates spool space, each volume used will correspond to a bit set in the mask. The job will be forced to use only volumes listed in the mask. Minimum fencing is defined as setting the volume limit to "1".
- **MAS member association:** Each spool volume has masks of systems that can allocate space on that volume. Jobs will be limited to the spool volumes associated with a system. You assign spool volumes to particular systems by using the \$T SPOOL command (there are no initialization options to do this.).

You must assess the benefits and drawbacks of spool partitioning and determine whether it would be to your advantage to use it in your spooling environment. Not using spool partitioning at all can provide increased performance because all jobs can allocate space on all volumes. However, not using spool partitioning can also cause severe performance degradation in some cases. For example, if frequently-referenced and long-running jobs are spread across all spool volumes your system might experience spool contention.

In most cases, using spool partitioning increases hardware processing reliability and is more likely to increase performance if you correctly isolate frequently-referenced jobs. Review the following sections, the descriptions of the initialization parameters controlling spool partitioning in *z/OS JES2 Initialization and Tuning Reference*, and the material concerning Exits 11 and 12 in *z/OS JES2 Installation Exits* before using these facilities to modify your spooling environment.

Each of the initialization statements and the installation exits affecting spool partitioning, their interaction, and some examples of that interaction are provided.

Using the FENCE Parameter to Partition Spool Volumes

The FENCE parameter on the SPOOLDEF statement further defines the spooling environment by controlling the partitioning of the spool volumes. You use the FENCE parameter to tell JES2 how to partition spool volumes when performing I/O operations. If fencing is turned off then jobs that have already obtained some spool space when fencing was active will not be fenced. Use FENCE=(ACTIVE=YES,VOLUMES=nnn) to indicate that all space that a job requires will be allocated from "nnn" volumes. (FENCE=(ACTIVE=YES,VOLUMES=1) is equivalent to FENCE=YES in prior releases.) These volumes are determined by JES2 as the first available volume from which this job can allocate space; this is determined by the setting of the spool partitioning mask work area. The spool partitioning mask is set with bits on to indicate the spool volumes from which the job can allocate space. If you specify FENCE=(ACTIVE=NO,VOLUMES=nnn), the spool partition mask will not indicate any available volumes (no bits are set on). JES2 sets all the bits on (indicating that all volumes are usable) and no spool partitioning is permitted; the space these jobs require is allocated across all available spool volumes.

Although, FENCE=(ACTIVE=YES,VOLUMES=nnn) indicates that JES2 will fence to nnn volumes in most cases. However, more than one nnn volume may be used in

certain situations (when spool volumes fill or if the job obtains spool space on different systems as it goes through different phases.) JES2 will allocate space from a subsequent volume(s) when, and if, the "nnn" becomes full. At that time, JES2 will allocate track groups from the next available volume based on any other criteria that you have defined.

Associating spool volumes with MAS members: JES2 uses a control block, the BLOB, to provide rapid access to spool space for running jobs. By associating spool volumes to systems in a mask, there will be a limit to the entries the BLOB can hold.

For example, you have a MAS where

```
SPOOLDEF FENCE=(ACTIVE=YES,VOLUMES=2)
```

is specified. Member A has spool affinity for volumes 1,2, and 3. Member B has spool affinity for volumes 1,2, and 4. A job converts on Member A and uses volumes 1 and 3. The job then executes on Member B. The job will potentially use space from three volumes before the fencing limit of 2 is reached. Since Member B does not have affinity for volume 3, the job will be allowed to get spool space from Volume 1 and either Volume 2 or 4 before the fencing limit is reached. A similar situation to this could occur if all spool volumes with affinity for the member temporarily fill and a job begins using space from a volume without affinity for the member.

Refer to the FENCE= parameter on the SPOOLDEF statement in *z/OS JES2 Initialization and Tuning Reference* for how to use this parameter.

Further refinement of spool volume selection can be accomplished with use of JES2 installation Exits 11 and 12. See *z/OS JES2 Installation Exits* for information about these exits.

Allocating Tracks and Track Cells

You can specify the manner in which the tracks of the volumes are allocated and subdivided into physical records by specifying the BUFSIZE=, TGSPACE=(MAX=), and TGSIZE= parameters on the SPOOLDEF initialization statement.

The tracks are also subdivided into track cells, which are sets of JES2 buffers (physical records) grouped together on a spool volume in a logical order. Indicate the number of records in each track cell by specifying the TRKCELL= parameter on the SPOOLDEF statement during initialization. If the track-cell method is used for despooling data, each track cell that is to be sent to a printer, rather than each spool buffer, can be taken from the spool volume in one operation; thus, it is not necessary to have a separate I/O operation for each spool buffer.

Handling Defective Track Groups

JES2 isolates bad track groups encountered on JES2 spool volumes. When an unrecoverable I/O error occurs, the operator receives message \$HASPO94 that identifies the address of the track where the error occurred. During purge processing, track groups that are allocated to the job or data set are normally returned to the pool of available track groups; the defective track groups are not returned. To return a defective track group to service, JES2 attempts to recover that track group. If the recovery is successful for all the tracks on a track group, that track group will be returned to service. The verification takes place when the job that encountered the I/O error is purged and during a warm start. To remember bad tracks across a cold start, you can identify them with the BADTRACK initialization statement(s).

Dynamic Addition and Deletion of Spool Volumes

The spool is the repository for all input jobs and most system output (SYSOUT) that JES2 manages. Due to fluctuating workload requirements, such as month-end processing, your installation might need to add spool space, or for maintenance reasons such as I/O errors, hardware failure, or utilization needs, you might need to delete idle spool packs. In order to optimize system availability, JES2 provides a facility to dynamically add and delete spool data sets. Through the use of operator commands (\$S SPL, \$P SPL, and \$Z SPL) spool data sets might be added or deleted without interrupting JES2 processing.

Spool data sets can be managed by the operator without affecting the normal processing of work, or any accompanying online system or processor availability. Therefore, the operator has the flexibility of adding or deleting spool data sets to meet your installation's varying workload needs. This facility permits multiple addition and deletion of spool data sets simultaneously, provided the maximum of 253 spool data sets is not exceeded at any one time. (Your maximum number of data sets can be less than 253. This number is dependent upon your JES2 track group size, JES2 buffer size, and the amount of space allocated on each spool data set.)

At a cold start, all mounted volumes whose first four or five characters match the VOLUME= parameter on the SPOOLDEF statement and contain the JES2 data set SYS1.HASPACE are automatically started. Spool volumes that do not contain the SYS1.HASPACE data set that are required for processing can be started dynamically in the future by use of the operator commands after the SYS1.HASPACE data set has been added to that volume.

Following a warm start, the status of the spool configuration is restored. A spool data set can be deleted at an all-member warm start if that data set is not available (for example, the volume is not mounted). However, if you delete a spool data set during an all-member warm start, you will lose all work which resides on those spool data sets (which can include: JESNEWS and spooled messages). If the data set is put into **inactive** status by the operator response (GO) to the \$HASP853 message, all work on that data set can later be recovered by the \$S SPL command. However, if the data set is **drained** by the operator response (PURGE) to the \$HASP853 message, all work on that data set is purged.

The operator can use the \$D SPL command to display the status of the data set and the jobs currently using a specific data set. The operator should be aware of the contents of a spool data set before deleting it. The deletion of a spool volume will not complete while jobs allocated to that volume are active in one of the phases of job processing. For example, if jobs allocated to the volume are in execution, the deletion command will not complete until the job finishes execution. Never- or seldom-ending jobs such as SYSLOG, IMS, CICS* and VTAM generally must be given special consideration. You must establish procedures to prevent such situations from occurring, and, if appropriate, establish procedures to handle redistribution of long-running jobs and system data sets. Refer to "Performance Considerations" below for the description of **device partitioning** procedures. Additionally, the \$D J,SPOOL command will display those data sets which are currently allocated to specific jobs.

Status of Spool Volumes

A spool volume is classified as having one of six status types, dependent upon whether it can be used to perform work and its ability to allocate or deallocate spool space. These status types and their definitions are presented in Table 45 on page 172.

Table 45. Spool Volume Status Types and Definitions

Status	Explanation
ACTIVE	The spool volume is in use. Allocation and deallocation of spool space is permitted. The volume is allocated to all systems in the multi-access spool complex.
STARTING	The spool volume is not yet ACTIVE. It is in the process of dynamic allocation or formatting. During this time, the volume is being dynamically allocated to each system in the multi-access spool complex. Allocation or deallocation of spool space is not permitted.
DRAINING	Jobs already residing on the volume are selectable for processing; also deallocation of spool space is permitted. Allocation of new spool space is not permitted. The volume must be completely empty before the drain process can complete. When the volume is completely empty, the volume will be dynamically unallocated to all systems in the multi-access spool complex. The spool volume then becomes DRAINED.
DRAINED	The spool volume is completely empty and unallocated, that is, no allocated spool space remains on the volume, and the volume is unallocated to all systems in the multi-access spool complex. The volume is no longer known to JES2.
HALTING	The spool volume stops allocation of space and does not select new work. Currently active work (that is, executing, printing, punching, etc.) is allowed to complete that phase. When all currently active work on the volume completes, the volume will be dynamically unallocated to all systems in the multi-access spool complex. The spool volume then becomes INACTIVE.
INACTIVE	The spool volume can contain allocated tracks, but does not permit further allocation or the processing of currently allocated tracks. The volume has been unallocated on all systems in the multi-access spool complex and can be removed by the operator.

Table 46 summarizes the characteristics of the six status classifications of spool volumes:

Table 46. Summary of Spool Volume Status Characteristics

STATUS	IN USE*	ALLOCATABLE**	SELECTABLE***
STARTING	No	No	No
ACTIVE	Yes	Yes	Yes
DRAINING	Yes	No	Yes
DRAINED	No	No	No
HALTING	Yes	No	No
INACTIVE	No	No	No
* IN USE - Active jobs are using space on the volume ** ALLOCATABLE - New spool space can be allocated on a volume *** SELECTABLE - Jobs that have space on a volume can be selected for JES2 processing.			

Addition of Spool Volumes

Spool volumes are added either at a cold start or dynamically through use of operator commands (refer to *z/OS JES2 Commands* for specific use of these commands). You can define a maximum of 253 spool volumes to JES2 at any one

time. If the dynamic addition of another spool volume is attempted (thereby exceeding the maximum of 253 spool volumes) the command will be ignored, the volume will not be added, and message \$HASP411 will be issued to the operator.

If however, the maximum of 253 spool volumes is exceeded during a cold start, JES2 issues a message informing the operator that more spool volumes were found than expected from the SPOOLNUM= specification on the SPOOLDEF initialization statement. Then, the operator can determine whether or not to end initialization. JES2 ends. To display the contents and count the number of defined spool volumes the operator can issue the \$D SPL, ALL command. All volumes listed (to include those in **draining** status) should be included in your count. Only after such volumes are completely **drained** are they considered undefined to JES2.

The operator can issue the \$S SPL command to add (and format) a new spool volume or return an inactive volume to the configuration. During the addition phase of a spool volume, other processing within the system continues normally.

Deletion of Spool Volumes

Spool volumes can be deleted dynamically by the operator as required to meet your installation's requirements. The operator can either halt (\$Z SPL) or drain (\$P SPL) entire spool volumes.

Some considerations must be recognized and proper precautions must be taken to prevent improper usage of the spool volume deletion commands. If the volume being deleted (halted or drained) contains spooled or remote messages or the JESNEWS data set, they are automatically moved to another volume; however, this process might not be immediate. Spooled remote messages and SYSOUT are moved from the draining volume when they become the lowest-numbered job on the volume. Also, if there are no active volumes available for these data sets, the deletion process will not complete until an active volume is available to accept them.

The \$Z SPL command can be used to allow only currently active work to complete. No new work is selected, and no new tracks can be allocated. A volume is classified as **halting** until the currently active workload on the volume has completed the current phase of job processing and the volume is unallocated to all systems in the multi-access spool complex. Once complete, the volume is classified as **inactive**. However, the operator can display information about the volume or individual jobs on that volume. A \$S SPL command must be issued to bring the volume back into the JES2 environment.

The \$P SPL command prevents any available tracks from being selected for allocation. Until all jobs currently allocated to the volume have completed all phases of job processing the volume is considered to have a status of **draining**. The spool volume is **drained** when no allocated spool space remains on that volume, and the volume is unallocated to all systems in the multi-access spool complex. Once the spool volume is drained, JES2 does not retain any information concerning that volume. Therefore, the operator cannot display information about the volume.

The CANCEL operand can be added to the drain command (\$P SPL) to cancel and deallocate all cancellable jobs on either an **active** or **inactive** spool volume. All jobs and SYSOUT will be deleted from the volume; any spooled remote messages and the JESNEWS data set (if present) are automatically moved to another volume. As with the \$P SPL and \$Z SPL commands, the removal of these items might not occur immediately. Also, if any data sets residing on another volume belong to a job

being cancelled, they are also purged. Message \$HASP890 is issued to inform the operator of all such jobs. All other resources are recovered.

The \$P SPL,CANCEL command can also be used to drain an inactive volume, purging all jobs allocated to it. **This can result in lost track groups on other volumes.** Any lost space can be recovered at an all-member warm start or the JES2 automatic spool reclamation function will recover them within 1 week, whichever occurs first. If the spool volume can be remounted, the \$S SPL,P,CANCEL command will prevent the loss of spool space.

Before re-using a spool volume, you should erase (overwrite with binary zeroes) the volume. This avoids any inadvertent disclosure of classified information.

Attention: If *all* spool volumes are deleted, JES2 will not be capable of performing any work. For information concerning the use and syntax of the various operands that can be used with spool volume configuration commands, see *z/OS JES2 Commands*.

Performance Considerations and Recommendations

You need to be aware of several performance considerations when taking advantage of the dynamic addition and deletion feature of spool volumes. These are presented below with appropriate recommendations to avoid serious performance degradation.

Spool partitioning (that is, explicitly limiting or identifying the spool volumes from which a particular job is permitted to allocate track groups) can be a useful tool when future alteration of the spool configuration is anticipated. Because standard JES2 processing allows all jobs to allocate track groups on all available spool volumes, the deletion of a single volume can involve many jobs. Isolation to an installation defined number of volumes of long-running jobs (or jobs frequently put into hold status for long periods of time) to one spool volume (or as few as possible) can greatly facilitate future spool volume reconfiguration. If however, only particular volumes are allowed to allocate track groups to long-running jobs or jobs often put in hold status, for example, the status of other volumes can be changed as required more easily.

Use the IBM-supplied Exit 11 and Exit 12 to take full advantage of the dynamic addition and deletion of spool volumes without degrading performance. See *z/OS JES2 Installation Exits* for information about these exits.

The spool offload facility can also be used to facilitate the deletion of a volume. Jobs and SYSOUT residing on the volume to be drained can be offloaded to an offload data set, and reloaded at any future time. If needed, these data sets can be reloaded immediately; they will reside on other spool volumes because a halting or draining volume cannot allocate space. (Refer to “Spool Offload Facility” on page 178 and *z/OS JES2 Commands* for further information on the spool off-load facility.)

Recovering from Spool Volume Failure

If a spool failure occurs, JES2 halts all paths to each spool volume in error the next time data is requested from that system. If an I/O request to a spool volume fails for some other reason, you can enter the \$Z SPL command to halt the volume. JES2 allocates spool space from the active volumes only. When the installation performs an all-member warm start on all the active spool volumes, JES2 issues the \$HASP424 message to indicate that the halted spool volume is not mounted. Then JES2 issues the \$HASP853 message, to which the operator must reply GO, PURGE, or QUIT. Reply:

- GO if the volume can be recovered. JES2 mounts the volume in an inactive state: jobs previously allocated from this volume are not available for processing until the spool volume is started when an operator enters the \$S SPL command.

Note: If JES2 is interrupted during spool validation (through either an abnormal end or a re-IPL), JES2 does not provide the GO option to the operator.

- PURGE only if the spool volume is permanently damaged. JES2 removes all jobs with any space allocated from that volume.

Use this response only if the volume cannot be recovered; JES2 does not issue any messages to indicate that all these jobs have been purged from the system.

Note: If JES2 issues message \$HASP424 when recovering from a spool failure, generally, you will respond PURGE to \$HASP853. However, if you are uncertain if the volume is permanently damaged and want to keep the system running until you have verified its status, reply GO. If you later determine that the spool volume is lost, you can re-IPL and then reply PURGE to \$HASP853.

- QUIT ends JES2.

The **\$D JOBQ,SPL=(V=volser)** command displays all jobs currently allocated on the spool volume. If you enter GO in response to the \$HASP853 message, you can enter this command to examine the spool's contents once you have started the volume.

The **\$D A,ALL,X,DEV,VOL=volser** command displays all jobs that are active and have space on the spool volume.

Use the FENCE=(ACTIVE=YES,VOLUMES=nnn) option on both the SPOOLDEF initialization statement and the \$T SPOOLDEF command to minimize the effect of a permanently damaged spool on jobs in an installation. When FENCE=(ACTIVE=YES,VOLUMES=nnn) is specified, JES2 allocates all track groups for a job from the installation specified number of volumes. If the FENCE= parameter is not used, JES2 allocates track groups for each job from all volumes available in the installation. If a volume fails on an installation that does **not** use fencing, that installation is likely to lose the majority of jobs on spool. For more information, refer to "Using the FENCE Parameter to Partition Spool Volumes" on page 169.

In addition, JES2 installation exits 11 and 12 can limit the spool volumes from which a job can allocate space. For more information, see *z/OS JES2 Installation Exits*.

Spool Performance Considerations

You can improve the performance of spool data sets through:

- "Selecting Spool Devices"
- "Allocation of Spool Space" on page 176
- "Track Ceiling" on page 177.

Selecting Spool Devices

When selecting devices for spool volumes, consider that the volume(s) which contain JES2 control blocks, job input and output data, and spool message queue records (for remote terminals) should go on a device that has reasonable speed and good capacity, such as a 3390. Do not use DASD intended to transmit bulk data. SYS1.HASPACE is the default name of this data set; you can rename the

data set through the `DSNAME=` parameter on the `SPOOLDEF` initialization statement. You can define from 1 to 253 spool volumes with the name `SYS1.HASPACE` to use as JES2 spool. The `BUFSIZE=` parameter on the `SPOOLDEF` initialization statement defines the length of each record.

For best performance, it is desirable to dedicate spool volumes (that is, do not share a volume with paging data sets or other data sets). If there is more than one spool device, they should be put on separate channels. The channel need not be dedicated, however, because JES2 channel utilization is low. The `$S SPL,FORMAT` command, however, does result in extremely high channel utilization, but this is only a temporary condition, lasting for the duration of spool formatting.

You can enhance the performance of spool volumes through the use of cache controllers that provide high-speed buffered data. In particular, the 3990-3 cache controller provides JES2 spool volumes with:

- Larger cache memory sizes
- Non-volatile storage (allowing the high-speed buffering of DASD writes as well as DASD reads)
- Image copies of DASD devices.

The cache is a large electronic buffer that provides quick channel access for data that is currently in use and already stored on DASD. DASD Fast Write is a method of reading from and writing to the data stored in these caches. If you define spool volumes to enhance performance by spreading I/O across different volumes, DASD Fast Write allows you to define fewer large spool data sets without having high IOS queue times (the span of time between when a JES2 member requests IO and when that IO is processed). By reducing the amount of DASD supporting JES2, you can reduce costs at your installation.

Note: IBM recommends running RMF DASD reports to indicate JES2 spool volume performance.

Allocation of Spool Space

JES2 allocates spool space for a job by dividing each spool volume into track groups. A track group consists of one or more DASD tracks. JES2 allocates spool space to a job one track group at a time. When a given track group is exhausted, JES2 allocates the next track group as close to the perimeter of the device as possible on the spool volume. Track groups are obtained from eligible spool volumes on a rotational basis to balance spool I/O. Seek time is therefore minimized.

The `TGFSIZE=` parameter on the `SPOOLDEF` statement controls the number of JES2 buffers in a track group. JES2 uses this value to calculate the size (in tracks) of a track group for each spool device. Track group size is rounded to the minimum integral number of tracks that can contain `TGFSIZE` buffers (each set to the `BUFSIZE=` specification on the `SPOOLDEF` statement). In an environment with mixed spool devices, it is best to specify a value for `TGFSIZE=` that results in consistent spool space allocation for each job regardless of the device type.

Small values for `TGFSIZE=` might cause an excessive number of track group allocations per job. Large values for `TGFSIZE=` might waste spool space and increase seek time. Refer to the descriptions of `BUFSIZE=`, `TGFSIZE=`, and `TGSPACE=(MAX=)` parameters on the `SPOOLDEF` statement in *z/OS JES2 Initialization and Tuning Reference* for more information on the specification of

these parameters, allocation of spool space, and their relation to maximizing device utilization and overall system performance.

Track Celling

JES2 uses track celling to maximize its efficiency of performing I/O operations on the spool.

Track cells are sets of JES2 buffers, or track records, grouped together in a logical order on a track. The `TRKCELL=` parameter on the `SPOOLDEF` initialization statement indicates the number of records in each track cell. When track celling is used, each track cell that is to be sent to a printer, rather than each record, can be taken (despooled) from the spool volume in one operation. Track celling can be used to reduce spool contention. Note that track-cell despooling is used for local and functional subsystem (FSS) printers only; it is not used for remote job entry (RJE), network job entry (NJE), or the process `SYSOUT` (PSO) interface.

There are three ways JES2 performs despooing

- Single record reads (no track celling)
- Standard track celling
- Advanced track celling

Standard trackcelling is recommended particularly for high-speed printers operating under the control of a functional subsystem. This is particularly recommended for page-mode data sets that contain graphic images. However, track-cell despooing is not required or appropriate for low-speed printers such as the 3820. By not using track celling for these devices, considerable storage is saved in the FSS address space and in central storage. Therefore, JES2 sets the default for printers to not use track-cell despooing. If an installation requires the option, it must overtly request it by initialization statement, that is, you must add `TRKCELL=YES` to the `PRT(nnnn)` statement. To prevent performance degradation, `TRKCELL=YES` must be specified for all high-speed printers running under the control of an FSS.

Standard track celling can be used if the following two qualifications are met:

- The `SYSOUT` class must be one for which track celling was specified through the `OUTCLASS(v)` initialization statement.
- `TRKCELL=YES` must be specified for the printer on the `PRT(nnnn)` initialization parameter.

Both nonimpact and impact printers can have the track-cell despooing capability.

The standard track-cell method of despooing can affect the efficiency of both the system and the printers. A printer employing track-cell despooing fixes its buffers, as well as the channel program used to send the data from the buffers to the printer. This storage is not used for anything but sending output to the printer, thereby reducing the number of pages fixed and freed by the MVS system. (The size of this fixed storage area depends upon the `SPOOLDEF` statement parameters, `BUFSIZE=` and `TRKCELL=`.) If too high a value of `TRKCELL=` is specified, too much central storage capacity is lost because of the increase in the amount of fixed-buffer storage. This can result in decreased system performance.

Specification of `TRKCELL=` can potentially leave short track cells at the end of each track. These track cells will be allocated to data sets of a `SYSOUT` class that does not have the track-cell characteristic (`TRKCELL=NO`) specified on the `OUTCLASS(v)` statement.

If, after allocating as many track cells as possible per track, at least TRKCELL/2 records remain, then these remaining records are also considered to be a track cell. These **short track cells** detract from the full performance benefits of track celling, but they do allow greater utilization of DASD space. However, if after allocating as many track cells as possible per track, less than TRKCELL/2 records remain, then these remaining records may be allocated to non-track cell data sets within the job. But because these records have a rather high (job dependent) probability of not being assigned to non-track cell data sets, the underutilization of DASD space may result.

Ideally, specification of TRKCELL= should divide evenly into the number of records in a track group (TGSize=) for all spool volumes to provide the greatest DASD utilization. Refer to Appendix A for recommended TRKCELL= values based on device type.

When choosing a value for TRKCELL=, note that during print processing the value specified for TRKCELL= is also the number of JES2 buffers that will be fixed into central storage (twice as many are fixed when RDBLBUFR=YES parameter on the PRINTDEF statement is specified); these pages will not be available to the rest of the system for the duration of the output. These buffers would normally be fixed by the MVS I/O supervisor during print processing; however, to reduce the overhead of constantly fixing and freeing these pages, JES2 leaves them fixed.

Advanced track celling is an internal JES2 process of grouping track group buffer sets. Each set holds an entire track group worth of data, and JES2 reads the entire track group into a buffer. Also, SPIN data sets, SYSIN data sets, and SYSOUT data sets from NJE are candidates for both standard and advanced track celling.

Spool Offload Facility

Spool is the primary medium for all JES2 data. All input jobs and system output (SYSOUT) are stored on the spool. JES2 gives your installation the capability to offload (transmit) data from the spool to a data set and later reload (receive) from the data set to the spool. The spool offload facility uses either tape or DASD as the offload medium.

Spool offload eases the migration from release to release by lessening the impact of a cold start. The facility provides a release-independent means of moving the data on the spool between releases.

Note that spool transmissions can contain clear text versions of all JOB statements. *If they are not properly secured, unauthorized discovery of RACF userid and passwords could occur.*

Overview

The spool offload facility is useful when performing the following tasks:

- Preserving pre-execution
- jobs and SYSOUT across a cold start by migrating your installation to another release of JES2.
- Relieving a full-spool condition during high-use periods; you can reload at a later time.
- Converting to another DASD type for spool.
- Backing-up spool data sets.
- Backing-up NJE connections.

The following topics explain how to use the spool offload facility, providing details on:

- “Defining the Offload Facility”.
- “SMF Record Summary: Transmitting and Receiving Jobs and SYSOUT” on page 181.
- “Offloading All Pre-Execution Jobs and SYSOUT” on page 182.
- “Reloading All Pre-Execution Jobs and SYSOUT” on page 186.
- “Offloading Selected Jobs and SYSOUT” on page 188.
- “Reloading Selected Jobs and SYSOUT” on page 190.
- “Using the Spool Offload Facility for Networking” on page 192.

Defining the Offload Facility

Spool offload uses the order and format of NJE records and BSAM (Basic Sequential Access Method) processing to perform I/O to either tape or DASD data sets. Transmitter and receiver logical devices act as a connection between the spool and the offload data set, passing noncompressed data back and forth. It is possible to have more than one transmit or receive operation active at a time. You should make sure to protect offloaded data by defining the offload data set to RACF. During the offload process RACF ensures that the owner of the SYSOUT data has access to the offload device and on reload ensures that the proper data is reloaded before writing it to spool. You must ensure that your local node is defined to RACF, so that your SYSOUT is reloaded with the proper userid. For more information, see “Protecting Spool Offload Data Sets” on page 362.

You can use the following five statements to define the logical offload devices:

- OFFLOAD(n)
- OFF(n).JT
- OFF(n).ST
- OFF(n).JR
- OFF(n).SR

The OFFLOAD(n) statement defines the logical offload device that is associated with the offload data set(s). Jobs and SYSOUT are transmitted to and from a data set specified by the DSN= parameter of the OFFLOAD(n) statement. You must specify this initialization statement to use the spool offload facility. This statement is numbered to correspond to the offload transmitter statements. You can define up to eight offload devices per system by the OFFLOAD(n) statement. However, only eight offload devices can be active within a multi-access spool complex at a time. An offload device started on one member of a multi-access spool complex cannot also be started at a second member. If you attempt to do so, JES2 issues the \$HASP593 message, indicating that the start has been rejected because the device is already in use.

The four statements listed above collectively control the transmitting and receiving of offload data. If you do not include transmitter and receiver statements following the OFFLOAD(n) statement, JES2 creates them for you. That is, JES2 provides four default statements: a job transmitter, a job receiver, a SYSOUT transmitter, and a SYSOUT receiver. JES2 provides default parameters values, but does not set parameters without defaults.

To control the transmission of jobs and SYSOUT that you intend to offload, use the OFF(n).JT and OFF(n).ST initialization statements respectively. For example, the statement parameters can control the transmitting of only specific classes, range of jobs, processing mode, or route code. (Refer to *z/OS JES2 Initialization and Tuning Reference* for a more complete description of each statement.)

To control the receiving of offloaded jobs and SYSOUT, use the OFF(n).JR and OFF(n).SR initialization statements respectively. As with job and SYSOUT transmitters, refer to *z/OS JES2 Initialization and Tuning Reference* for a complete description of what work selection criteria you can control.

Selecting Jobs and SYSOUT Through Work Selection

JES2 provides the WS= parameter on many device initialization statements to allow you to control output selection. Before using the work selection subparameters described below, see *z/OS JES2 Initialization and Tuning Reference*.

If printers can select the same work as offload devices, the printers and offload devices compete for the work. If a printer gains access first, it purges the data set or output group if its output disposition (OUTDisp=) is either PURGE or WRITE, making its SYSOUT unavailable for transmitting to an offload data set.

JES2 provides two methods for avoiding such device competition:

1. Creating multiple print instances for each piece of output
2. Printing the output, then creating another copy.

For both methods, installations must establish a policy they can enforce to ensure that the JCL used to submit jobs specify particular work selection characteristics. Such a policy ensures that installation devices select the proper output.

You can create multiple print instances for each piece of output by specifying a different route code (RouteCode=), writer name (Writer=), or any other work selection characteristic for the printer and the offload devices. Then JES2 is aware that, until both devices have processed this SYSOUT, the data set cannot be purged.

Use the following JCL sample to exploit this alternative:

```
//smpjcl JOB ....
:
//PRTOUT OUTPUT DEST=LOCAL
//OFFLOAD OUTPUT DEST=TAPE01
:
//DD1 DD SYSOUT=A,OUTPUT=(*.PRTOUT,*.OFFLOAD)
```

At a minimum, IBM recommends defining one offload device for selective offload and another offload device for total spool offload.

An installation can also ensure that all output has printed, then create another copy of the output by specifying OUTDISP=KEEP on all output. Once a printer has selected an output group, that output group's disposition changes to LEAVE. Then you can specify OUTDISP=LEAVE on the offload device and change the output's disposition to purge by specifying DISP=DELETE on the OFF(1).xT initialization statement, where x specifies either a job or SYSOUT transmitter.

Note: Regardless of how you avoid device contention, remember that all output must print to ensure that it is not lost in the event of a spool volume failure.

Using Uncataloged Data Sets

If you are offloading to DASD, you should pre-allocate the data set because you cannot specify the SPACE= parameter on the OFFLOAD initialization statement. If the output data set has not been pre-allocated and pre-cataloged, you can use the OFFLOAD(n) initialization statement to define the tape unit on which the data set(s) will be defined and specify the tape label and security information about the data sets. The following OFFLOAD(n) parameters specify:

- LABEL= the type of label processing for the specified tape.

- PROTECT= whether the data set receives System Authorization Facility (SAF) protection.
- RETPD= the number of days JES2 retains the tape.
- UNIT= provides either a unit address, device type, or group name (to specify a general group of devices) on which JES2 writes the data set. The second value on this parameter defines the number of devices JES2 allocates to the data set.

The use of these OFFLOAD initialization statement parameters will free the operator from additional involvement whenever a new offload data set is created.

Using Pre-cataloged Data Sets

If you use a tape management system, you should not pre-catalog tapes for the spool offload facility. If you pre-catalog a tape with a data set name and a tape catalog that have no match in the MVS system catalog, JES2 ends the program abnormally with an 8FB reason code and issues the \$HASP078 message.

If you use pre-cataloged data sets, JES2 ignores any parameters you might have specified on the OFFLOAD(n) initialization statement. If the UNIT= parameter is ignored, you could overwrite another data set of the same name. Make sure the spool offload data set defined on the OFFLOAD(n) DSN= statement matches the data set you have cataloged.

JES2 limits pre-cataloged data sets to a 20-volume multi-volume expansion. When preparing to offload jobs and SYSOUT, make sure the data being offloaded does not require more than this limit. If you exceed the number of volumes, JES2 responds with an allocation abend. For example, if you pre-allocate and pre-catalog the offload dataset and you specify 6 volumes in the allocation, you can expand up to 20 volumes. JES2 would abnormally end after the twentieth volume.

If you pre-allocate a spool offload data set, JES2 always uses the following data set attributes:

- Undefined record format (RECFM=U)
- 4042-byte block size (BLKSIZE=4042).

If you specify different values for these attributes, JES2 ignores them.

The offload data set is dynamically allocated by JES2 when the operator specifies that transmitting or subsequent receiving is to begin. JES2 supports simultaneous transmitting to and receiving from different offload data sets.

SMF Record Summary: Transmitting and Receiving Jobs and SYSOUT

The following lists the SMF record written when transmitting or receiving jobs and SYSOUT. For a complete list of the record contents, see *z/OS MVS System Management Facilities (SMF)*.

Table 47. SMF Records Used by JES2 Spool Offload Facility

Record Number	Action that Causes the Record to be Written
24	<ul style="list-style-type: none"> • JES2 writes a pre-execution job to an offload data set successfully. • JES2 writes a SYSOUT data set to an offload data set successfully. • JES2 reads a pre-execution job from an offload data set successfully. • JES2 reads a SYSOUT data set header from an offload data set successfully.

Offloading All Pre-Execution Jobs and SYSOUT

Offloading jobs and SYSOUT from the JES2 spool to a sequential data set requires the operator to complete a 5-step procedure:

1. Display the job output forms queue, information about active jobs, and the number of jobs queued on the current spool.
2. Display the offload device's characteristics and the status of its transmitters and receivers.
3. Set and verify the logical offload data set.
4. Start offloading both jobs and SYSOUT.
5. Stop the offload device when all transmitters are inactive and the transmission is complete.

The following explains each step in this procedure, as well as the JES2 processing considerations that apply.

1. Display the job output forms queue, information about active jobs, and the number of jobs queued on the current spool.

You can use SPOOL Display and Search Facility (SDSF) or the following JES2 commands to display the current status of jobs on spool. Performing this task before offloading ensures that you have data to compare when you display the contents of the new spool after reloading.

Command

Console Display

- \$D N** Displays job queue information about jobs processed on the spool offload device.
- \$D F** Displays the job output forms queue.
- \$D OJ** Displays the output processing characteristics of individual job output elements.
- \$D Q** Displays the number of jobs on a queue and the percentage of spool use.

Note: Because the system is not quiesced, the status of jobs on spool can change before you begin offloading jobs.

2. To display the offload device's characteristics and the status of its SYSOUT transmitters (ST), SYSOUT receivers (SR), job transmitters (JT), and job receivers (JR), enter the command:

```
$D U,OFFLOAD1
```

Through this command, you must ensure that the devices display **STATUS=STARTABLE**; which indicates that the devices are drained and ready to begin offloading jobs and SYSOUT. The offload transmitter you intend to use must be drained. Note that Figure 32 on page 183 displays devices that are drained and available to begin offloading jobs and SYSOUT.

```

$DU,OFFLOAD1
$HASP882 OFFLOAD1 740
$HASP882 OFFLOAD1 DSN=BECKER.DUMPER01,STATUS=DRAINED,LABEL=SL,
$HASP882 PROTECT=NO,RETPD=0,UNIT=(,1),VOLS=255
$HASP884 OFF1.JT 741
$HASP884 OFF1.JT STATUS=STARTABLE,CLASS=B,CREATOR=,
$HASP884 DISP=DELETE,HOLD=,JOBNAME=,NOTIFY=NO,RANGE=(J
$HASP884 1,65534),ROUTECD=(),START=YES,SYSAFF=(),
$HASP884 VOLUME=(,,),WS=(CL/)
$HASP886 OFF1.ST 742
$HASP886 OFF1.ST STATUS=STARTABLE,CREATOR=,DISP=DELETE,
$HASP886 OUTDISP=(WRITE,KEEP),HOLD=,JOBNAME=,
$HASP886 NOTIFY=NO,RANGE=(J1,65534),ROUTECD=(),
$HASP886 START=YES,VOLUME=(,,),WS=(Q/),BURST=,FCB=,
$HASP886 FLASH=,FORMS=,LIMIT=(0,*),PLIM=(0,*),
$HASP886 PRMODE=(),QUEUE=X,UCS=,WRITER=
$HASP883 OFF1.JR 743
$HASP883 OFF1.JR STATUS=STARTABLE,CLASS=,CREATOR=,HOLD=,
$HASP883 JOBNAME=,MOD=(CLASS=,HOLD=,ROUTECD=,
$HASP883 SYSAFF=),NOTIFY=NO,RANGE=(J1,2147483647),
$HASP883 ROUTECD=(),START=YES,SYSAFF=(),WS=(/)
$HASP885 OFF1.SR 744
$HASP885 OFF1.SR STATUS=STARTABLE,
$HASP885 OUTDISP=(WRITE,HOLD,KEEP,LEAVE),CREATOR=,
$HASP885 HOLD=,JOBNAME=,MOD=(BURST=,OUTDISP=,FCB=,
$HASP885 FLASH=,FORMS=,HOLD=,PRMODE=,QUEUE=,ROUTECD=,
$HASP885 UCS=,WRITER=),NOTIFY=NO,RANGE=(J1,2147483647),
$HASP885 ROUTECD=(),START=YES,WS=(Q/),BURST=,FCB=,
$HASP885 FLASH=,FORMS=,PRMODE=(),QUEUE=X,UCS=,WRITER=

```

Figure 32. Display of Offload Devices

If no offload devices are available, you can wait for the device currently being used, or enter the following command to close, dynamically deallocate, and stop the selection process of the offload data set:

```
$P OFFLOAD1
```

Note that if your installation uses one offload data set to back up the primary offload data set, closing the data set would eliminate the back-up offload device. This command should be used with caution.

If you define at least two offload devices and reserve one for offloading the entire spool, an installation can:

- Avoid having to change the work selection criteria through operator command
- Ensure that no jobs or SYSOUT are lost in the transition from the spool volume to another offload data set.

Reserve one offload transmitter to transmit all pre-execution jobs and SYSOUT to the offload data set by specifying

```
WS=(/)
```

in the initialization stream for the OFF(n).JT and OFF(n).ST initialization statements. Note that this form of offloading does not avoid the device competition problem mentioned in “Selecting Jobs and SYSOUT Through Work Selection” on page 180. To avoid device competition with this method, you must ensure that no other devices can select data while the transmitter is offloading.

If the transmitters do not display WS=(/), you must remove the specified work selection criteria through the modify offload command.

Enter the following command:

```
$T OFF(1).xT,WS=(-c/-c)
```

where **x** indicates a Job (J) or SYSOUT (S) transmitter and **c** indicates the specific criteria being removed. JES2 transmits both held and non-held jobs, and SYSOUT.

3. Set and verify the logical offload data set. If you are using a pre-cataloged data set, ensure that the displayed data set is the appropriate data set for the offload task. If not already specified, set the data set name by entering:

```
$T OFFLOAD1,DSN=dsname
```

where **dsname** is the name of the sequential data set to receive the transmitted spool data.

This command allows an operator to change the name of an offload data set **before** it is allocated to an offload device.


If you do not use pre-allocated, pre-cataloged data sets, JES2 dynamically allocates them. You must tell JES2 where to place the dynamically allocated data set(s) through the UNIT= parameter of the OFFLOAD statement. **If you do not provide a UNIT= specification, JES2 is unable to proceed with dynamic allocation.** This dynamic allocation facility is only valid for \$S OFFLOADn,TYPE=TRANSMIT commands.

4. To begin offloading jobs and SYSOUT, enter the command:

```
$S OFFLOAD1,TYPE=TRANSMIT
```

Note that the offload data set is overwritten each time you enter this command. Therefore, nothing is saved on the offload data set.

You must start the offload device before its associated transmitters and receivers can be activated. Figure 33 on page 185 provides an example of the interaction of the offload transmit function and the required initialization statements. Note that OFF(n).JT and OFF(n).ST, device statements that are offloading from the JES2 spool (SYS1.HASPACE) to the sequential data set (specified by the OFFLOAD1 statement) are numbered “1” in this example.



OFFLOAD transmitters are used to transmit (offload) jobs and SYSOUT to an offload data set.

Figure 33. Offload Initialization Statements and `$$ OFFLOADn,TYPE=TRANSMIT` Relation

When transmissions are complete and devices have become inactive, JES2 issues the \$HASP524 message for job transmitters and the \$HASP534 message for SYSOUT transmitters.

5. To stop the offload device when the job and SYSOUT transmitters are inactive and the transmission is complete, enter the command:

```
$P OFFLOAD1
```

This command causes the offload data set to be closed and dynamically deallocated. Then, it stops the selection process of its associated transmitters and receivers.

If you fail to enter this command, the transmitters remain active and continue to select jobs and SYSOUT as they become available on the system.

Job Disposition

Installations can specify the disposition of both jobs and SYSOUT processed by the offload facility. Specify this disposition on the `DISP= KEEPIHOLDDELETE` parameter of the `OFF(n).JT` and the `OFF(n).ST` initialization statements. If you allow the `DISP=` parameter on these statements to default, JES2 deletes the selected output groups after they have been offloaded to the offload data set. Modify the disposition through the `$T OFF(n).JT,DISP=` and the `$T OFF(n).ST,DISP=` operator commands. You can specify the following for the `DISP=` parameter:

- **KEEP** specifies that the job or SYSOUT remains on the current queue following the offload transmit operation. The same offload device (for example, `OFF.xT1`) can never select this piece of work; however, another offload device (for example, `OFF.xT2`) can select it.
- **HOLD** specifies that the job or SYSOUT remains on the current queue after the offload transmit operation, however, the job is marked held at that time.

Note: An operator can change this disposition through the \$A J command and the \$T O,J command.

- DELETE specifies that the job or SYSOUT is purged after the offload transmit operation.

By using KEEP or HOLD, the spool offload facility is useful as an archival system: both the job and SYSOUT remain on spool and a copy is written to the offload data set.

Reloading All Pre-Execution Jobs and SYSOUT

The following procedure describes how to reload (receive) data onto a spool volume. Reloading all jobs and SYSOUT from the sequential data set onto the JES2 spool requires the operator to complete a 4-step procedure:

1. Display the offload receiver's characteristics.
2. Set and verify the logical offload data set.
3. Receive pre-execution jobs and SYSOUT onto the new spool data set.
4. Display the job output forms queue, information about active jobs, and the number of jobs queued on the new spool data set.

Before beginning this task, consider JES2 naming conventions and spool allocation practices. The node name of the system that performed the offload (transmit) procedure should be known to the system performing the reload (receive) procedure. If not, routing of jobs and SYSOUT can be unpredictable on the reloading system. Any unresolved routing results in jobs and SYSOUT executing and printing locally. Because JES2 does not allocate spool space for jobs that have already been processed, the percentage of spool utilization on a reloaded spool volume is often less than it had been on the old spool volume.

The following explains each step in this procedure, as well as the JES2 processing considerations that apply.

1. To ensure that the work selection parameter (WS=) is empty so that all jobs and SYSOUT can be read onto the spool volume, display the offload receiver by entering:

```
$D OFF1.xR
```

where **x** indicates either the job (J) or the SYSOUT (S) receiver. If the work selection parameter is empty, proceed to the next step.

If the work selection parameter has values, you must use the \$T OFFn.xR to remove these values.

Enter the following command:

```
$T OFF(n).xT,WS=(-c/-c)
```

where **x** indicates a Job (J) or SYSOUT (S) transmitter and **c** indicates the specific criteria being removed. JES2 transmits both held and non-held jobs, and SYSOUT.

2. Set and verify the logical offload data set. Ensure that the correct data set (DSN=) is used for the receive process. If it is not, set the data set name by entering


```
$T OFFLOAD(n),DSN=dsname
```

where **dsname** is the name of the sequential data set that contains the spool data for reloading.

3. To receive jobs and SYSOUT that have been offloaded to the offload data set onto the new spool volume, enter
`$$ OFFLOAD1,TYPE=RECEIVE`

This command directs JES2 to reload the data set based on the OFF(n).JR and OFF(n).SR initialization statement specifications. Just as the transmitter statements control what jobs and SYSOUT are offloaded, these two statements control what jobs and SYSOUT are received. Number these job/SYSOUT receivers to correspond to the OFFLOAD(n) statement.

Figure 34 provides an example of the receive function, showing how the required initialization statements interact. Here, the offload receiver statements, OFF(n).JR and OFF(n).SR, specify the data sets and jobs to be received. You must also number this set of receiver statements alike. As many as eight sets of receiver statements can be specified to correspond to the offload data sets specified by the OFFLOAD(n) statement. Note that in this example, OFF(n).JR, OFF(n).SR, and OFFLOAD(n) are numbered “1” to reflect a specific logical device and its corresponding transmitters and receivers.



OFFLOAD receivers are used to receive (reload) jobs and SYSOUT to an offload data set.

Figure 34. Offload Initialization Statements and \$\$ OFFLOADn,TYPE=RECEIVE

JES2 calls the security authorization facility (SAF) to verify that a userid is valid and has access to data with specific security labels. If you are reloading data from a release prior to SP 3.1.3, JES2 only verifies the userid.

The receiving system assigns a new date and time to the SYSOUT upon reload.

Unlike the offload (transmit) operation, when both SYSOUT and job receivers are inactive, JES2 drains these devices automatically. The \$HASP097 message appears when these operations complete.

4. Ensure that all jobs queued on the spool that held the data before it was transmitted to the offload data set have transferred cleanly to the new spool. See 182 for the list of commands or refer to *z/OS JES2 Commands*.

When ensuring that all data has been correctly reloaded to spool, you should note that job IDs are preserved from one spool to another, as long as the job number is not already assigned, and either the job number is inside the JOBDEF RANGE, or RASSIGN=YES. (The default is RASSIGN=YES.) Otherwise a new job ID is assigned from available job numbers within the JOBDEF RANGE.

Offloading Selected Jobs and SYSOUT

Offloading selected jobs and SYSOUT from the JES2 spool to a sequential data set requires the operator to complete a 5-step procedure:

1. Display the job output forms queue, information about active jobs, and the number of jobs queued on the current spool.
2. Display the offload device's characteristics and the status of its transmitters and receivers.
3. Set and verify the offload characteristics.
4. Start the offload device to begin offloading selected data.
5. Stop the offload device when all transmitters are inactive and the transmission is complete.

JES2 offloads selectable SYSOUT (ready data sets) by default if output disposition is specified in the SYSOUT transmitter work selection criteria (WS=OUTDisp). However, you can offload held SYSOUT data sets by specifying OFF(n).ST OUTDisp=HOLDILEAVE.

The following explains each step in this procedure, as well as the JES2 processing considerations that apply to offloading data selectively.

The spool offload facility supports selective offloading of pre-execution jobs and SYSOUT from the spool to offload data sets through the work selection (WS=) parameter. As devices select work selection criteria, so do spool offload devices. These work selection criteria are the same as those used by local and remote printers and punches to select work.

JES2 offloads all selectable work (ready data sets) by default, but can offload held data by specifying OUTDisp=(HOLD,LEAVE) on the OFF(n).ST initialization statement. Specify these selection criteria on the job transmitter and receiver statements during JES2 initialization. The 4 offload transmitter and receiver statements can be modified through \$T operator commands.

1. Display the job output forms queue, information about active jobs, and the number of jobs queued on the current spool.

You can use SPOOL Display and Search Facility (SDSF) or the following JES2 commands to display the current status of jobs on spool. Performing this task before offloading ensures that you have data to compare when you display the contents of the new spool after reloading.

Command

Console Display

\$D N Displays job queue information about jobs processed on the spool offload device.

\$D F Displays the job output forms queue.

\$D OJ Displays the output processing characteristics of individual job output elements.

\$D Q Displays the number of jobs on a queue and the percentage of spool use.

Note: Because the system is not quiesced, the status of jobs on spool can change before you begin offloading jobs.

2. To display the offload device's characteristics and the status of its transmitters and receivers, enter the command:

```
$D U,OFFLOAD1
```

3. To change work selection characteristics before transmitting jobs and SYSOUT to spool, enter the command:

```
$T OFF1.ST WS=(n)
```

where **n** is a work selection criterion.

The criteria that you can specify in a specific work selection (WS) list is individualized for the offload job and SYSOUT receivers and the offload job and SYSOUT transmitters. Refer to Table 48 on page 190 for the complete list.

You can tailor your offload procedure to filter based upon the work selection of your choice. If you want to offload SYSOUT based on queue selection, enter:

```
$T OFF1.ST WS=(Q/)
```

To offload SYSOUT based on job selection, enter:

```
$T OFF1.ST WS=(JOB/)
```

To offload jobs based on job name, enter:

```
$T OFF1.JT WS=(JOBNAME/)
```

If you find these selection criteria inadequate, you can create installation-defined work selection criteria through the \$WSTAB macro. (Refer to *z/OS JES2 Macros* for details on using this macro and extending this function.) You are limited, however, to a maximum of 19 WS criteria (USER and JES2 combined) for any one device.

Table 48. WS Criteria for Spool Offload Devices

Job Receivers	Job Transmitters	SYSOUT Receivers	SYSOUT Transmitters
<ul style="list-style-type: none"> • CLASS • CREATOR • HOLD • JOBNAME • RANGE • ROUTECDE • SYSAFF 	<ul style="list-style-type: none"> • CLASS • CREATOR • HOLD • JOBNAME • LIMIT • PRIORITY • RANGE • ROUTECDE • SYSAFF • VOLUME 	<ul style="list-style-type: none"> • BURST • CREATOR • FCBIC • FLASHIO • FORMS • HOLD • JOBNAME • OUTDISP • PRMODE • QUEUE • RANGE • ROUTECDE • UCSIT • WRITER 	<ul style="list-style-type: none"> • BURST • CREATOR • FCBIC • FLASHIO • FORMS • HOLD • JOBNAME • LIMIT • OUTDISP • PRIORITY • PRMODE • QUEUE • RANGE • ROUTECDE • UCSIT • WRITER • VOLUME

4. To begin offloading jobs and SYSOUT, enter the command:

```
$S OFFLOAD1,TYPE=TRANSMIT
```

Note: To change work selection characteristics after you have begun transmitting jobs and SYSOUT to spool, enter the command:

```
$Z OFFLOAD(1)
```

It halts an offload device temporarily, without deallocating the offload data set.

5. To stop the offload device when the job and SYSOUT transmitters are inactive and the transmission is complete, enter the command:

```
$P OFFLOAD1
```

Reloading Selected Jobs and SYSOUT

Reloading selected jobs and SYSOUT from a sequential data set to JES2 spool requires the operator to complete a 4-step process:

1. Display the offload receiver's characteristics.
2. Set and verify the logical offload data set.
3. Receive selected jobs and SYSOUT onto the new spool data set.
4. Display information about active jobs, the job output forms queue, and the number of jobs queued on the new spool data set.

The following explains each step in this procedure, as well as the JES2 processing considerations that only apply to offloading data selectively.

1. Display the offload receivers by entering:

```
$D OFF1.JR
```

and

```
$D OFF1.SR
```

2. Set and verify the logical offload data set. Ensure that the correct data set is used for the receive process. If it is not, set the correct data set name by entering:

```
$T OFFLOAD(n),DSN=dsname
```

where **dsname** is the name of the sequential data set that contains the spool data for reloading.

To further control the reload (receive) process, you can allow the job and SYSOUT receivers to modify some of the data set and job characteristics when the data sets and jobs are reloaded by entering the command

```
$T OFF1.XR,MOD=(...)
```

For available values, see the following figure.

Table 49. MOD Criteria for Spool Offload Receiving Devices

Job Receivers	SYSOUT Receivers
<ul style="list-style-type: none"> • CClass • Hold • Routecede • SYSaff 	<ul style="list-style-type: none"> • Burst • FCB • FLashIO • Forms • Hold • OUTDisp • PRMode • Queue • Routecede • UCS • Writer

3. To receive jobs and SYSOUT that have been offloaded to the offload data set onto the new spool volume, enter:

```
$S OFFLOAD1,TYPE=RECEIVE
```

Once reloaded, these data sets become automatically selectable for output processing to devices that were not originally able to select them. For example, you can set up the WS criteria for all printers and punches to select data sets with these “modified” characteristics. The MOD= parameter allows you to reload data sets originally assigned to a held class, and have JES2 change them automatically to nonheld status. Then change the class to one only selectable by a remote printer. As appropriate, the previously held SYSOUT are available to be selected by remote printers.

The range of selectable characteristics allows you to avoid reloading jobs or SYSOUT that waste spool space.

For more information on how to use the work selection parameters, see the following:

- “Variable Work Selection Criteria” on page 116
- Spool Offload initialization statements in *z/OS JES2 Initialization and Tuning Reference*

For more information about how to create installation-specific work selection criteria, see the following two sections in *z/OS JES2 Installation Exits*:

- “Defining JES2 Tables”
 - “JES2 \$SCAN Facility”
4. Ensure that all jobs queued on the spool that held the data before it was transmitted to the offload data set have transferred cleanly to the new spool. See on page 188 for the list of commands or refer to *z/OS JES2 Commands*.

Using the Spool Offload Facility for Networking

The spool offload facility provides a primitive form of job and SYSOUT transmission. By offloading a subset of jobs at one location and reloading them at another, the jobs will be effectively transmitted from location to location. Although this form of job networking is of limited value with widely separated machines, it is a possible alternative for NJE lines; you can offload spool files on one node, switch or physically transfer the offloaded data to the target JES2 system and use a spool offload receiver to reload the data.

In the example below, the local node offloads all jobs and SYSOUT with the route code SANJOSE. Once completed, this tape can be physically sent to the SANJOSE node. At SANJOSE operators can reload the tape, successfully transmitting the jobs.

```
$T OFF1.JT,R=SANJOSE,WS=(R)
$T OFF1.ST,R=SANJOSE.*,WS=(R)
$S OFFLOAD1,TYPE=TRANSMIT
$P OFFLOAD1
```

Figure 35. Offloading Data to Send to Another Node

Note: You cannot specify a second-level destination on a route code associated with pre-execution jobs.

Part 4. Checkpoint Data Set Definition and Configuration

Chapter 4. Checkpoint Data Set Definition and Configuration	195
JES2 Checkpoint Function	195
Placement of the Checkpoint Data Set.	196
Primary Checkpoint on a Coupling Facility Structure, Secondary	
Checkpoint on DASD	196
Both Checkpoints on DASD.	196
Benefits of Using a Coupling Facility	197
Checkpoint Data Set Specifications	197
CKPTn Data Set Definition and Placement on a Coupling Facility.	198
Recommendation for Initializing a Checkpoint on a Coupling Facility	
Structure	198
Ensuring the Integrity of Checkpoint Data.	198
CKPTn Data Set Definition and Placement on DASD	199
Controlling the Size of the Change Log	200
Storage Management Considerations on DASD	201
Determining the Size of Your Checkpoint Data Set	201
Determining the Current Checkpoint Size.	201
Determining the New Checkpoint Size	201
Allow Room for Dynamic Checkpoint Expansion	202
Step 1: Calculating 4K Records	202
Calculating the Number of 4K Records Needed	203
Sample Calculation	203
Step 2: Calculating the Checkpoint Size	204
Specifying the Storage of Checkpoints on DASD	204
Syntax for Checkpoint Space Allocation on DASD	205
Specifying the Storage of Checkpoints on Coupling Facility Structures	206
Approximate Storage Requirements on Coupling Facility Structures	206
Detailed Storage Requirements on Coupling Facility Structures	206
Placing a Checkpoint on a Coupling Facility for the First Time	207
Correcting a Structure Error of Size	207
Correcting a Structure Error of Incorrect Attributes	208
The Checkpoint Cycle	208
Checkpoint Cycle Overview.	209
Phase I - Checkpoint RESERVE, Lock, and Read	210
Phase II - Updating the Checkpoint	211
Phase III - Final Checkpoint Write and Data Set Release	211
Phase IV - Other Member Access	212
Checkpoint Configuration Modes	212
DUPLEX-Mode Processing (With Backup)	212
DUPLEX (With Backup) on DASD	212
DUPLEX (With Backup) on Coupling Facility	213
DUPLEX-Mode Processing (Without Backup)	216
DUPLEX (Without Backup) on DASD	216
DUPLEX (Without Backup) on Coupling Facility	216
Effects of Error Situations When DUPLEX=OFF	216
DUAL-Mode Processing	217
Example of DUAL Mode in a Two-Member MAS Configuration	217
Example of DUAL Mode in a Three-Member MAS Configuration	218
Accessing the CKPTn Data Set in a MAS	221
Controlled Checkpoint Data Set Access	221
HOLD= Parameter on the MASDEF Statement	221
DORMANCY=(mmmm,nnnn) Parameter on the MASDEF Statement	221
Member-Specific Parameter Recommendations	222

Contention-Driven Checkpoint Data Set Access	223
Replacement Data Set (NEWCKPTn) Definition	223
Space Allocation for NEWCKPTn Data Sets.	223
Specify the NEWCKPTn Data Set during Initialization	224
Specify the NEWCKPTn Data Set through the \$T CKPTDEF Command	224
Specify the NEWCKPTn Data Set during Reconfiguration (\$HASP271)	225
Specify the NEWCKPTn Data Set during Reconfiguration (\$HASP282)	225
Placement of the NEWCKPTn Data Sets	225
Using the NEWCKPTn Data Sets	225
Checkpoint Reconfiguration, An Overview	228
Checkpoint Reconfiguration Concepts	229
Preparing for Checkpoint Reconfiguration.	229
JES2-initiated Due to I/O Error	230
Predefining Replacement Checkpoint Data Sets	230
Using the Checkpoint Reconfiguration Dialog	230
Message Routing During a Checkpoint Reconfiguration	231
Determining the Reason for a Checkpoint Reconfiguration	231
Dialog Options: CANCEL and TERM	232
JES2-initiated Entrance into the Dialog	233
Initialization.	233
I/O Error.	234
Volatile Coupling Facility	237
Operator-initiated Entrance into a Checkpoint Reconfiguration Dialog	238
Replacing a Checkpoint Data Set	238
Discontinue Using a Checkpoint Data Set	239
Example Operator-initiated Reconfiguration Dialog	239
Checkpoint Reconfiguration Recovery	240
Driving Member Failure	240
Recovery from JES2 Member Failures.	240
Initiating Member(s) Failure in Start-up Processing	241
Member Delayed.	241
Clean-up After a Checkpoint Reconfiguration	241
Returning to Your Typical Checkpoint Data Set Definitions	241
Restarting JES2 from an Emergency Checkpoint	242
Making the Checkpoint Reconfiguration Definitions Permanent	243
Moving a JES2 Checkpoint to a Coupling Facility Using System Managed Rebuild	244
Recovering from Member Failures on Other JES2 Members.	245
Checkpoint on DASD	245
Checkpoint on Coupling Facility Structure	245
Using Operator Commands	246
JES2 Failure Only	246
MVS and JES2 Failure	246
Using the AUTOEMEM Option.	248
Enabling the JES2 AUTOEMEM Option at Initialization.	251
Providing Copies of the JES2 Checkpoint to Application Programs	252
Using Versions= to Provide Copies of the Checkpoint Data Set for Use by Applications.	253

Chapter 4. Checkpoint Data Set Definition and Configuration

JES2 Checkpoint Function

The JES2 checkpoint function performs two separate functions:

1. Job and output queue backup to ensure ease of JES2 restart
2. Multi-access spool (MAS) member-to-member workload communication to ensure efficient independent JES2 operation.

The function(s) the checkpoint data set will perform in your configuration depends on whether you have a JES2 single-member MAS, or a multi-member MAS with as many as 32 members.

Checkpointing is the periodic copying of a member's in-storage job and output queues to the **checkpoint** data set, which can reside on either a DASD volume or a coupling facility structure. Checkpointing ensures that information about a member's in-storage job and output queues is not lost if the member loses access to these queues as the result of either hardware or software errors. Because all members in a JES2 MAS configuration operate in a loosely-coupled manner, each capable of selecting work from the same job and output queues, checkpointing allows all members to be aware of current queue status.

Within the single-member environment, the checkpoint function operates solely as a backup to the "in-storage" job and output (SYSOUT) queues maintained by JES2.

In a MAS environment the checkpoint data set not only backs up the job and output queues, it also links all members. It is the commonly accessible repository of member activity that allows each member to communicate and be aware of the current work load. The checkpoint data set contains a record of member values that describe the overall configuration of the MAS environment and specific characteristics and information that describes the current status of each member. The checkpoint allows all members to access and update (write to) the checkpoint data set and also allows all members to refresh their in-storage queues by reading from the checkpoint data set.

The following discussion describes:

- "Placement of the Checkpoint Data Set" on page 196
This topic explains how workload performance can be enhanced by placing a checkpoint data set on a coupling facility structure rather than on DASD.
- "Checkpoint Data Set Specifications" on page 197
This topic explains how to specify your primary and secondary checkpoint data sets during initialization, using the CKPTDEF initialization statement for checkpoints that reside on both a coupling facility structure and on DASD.
- "Determining the Size of Your Checkpoint Data Set" on page 201
This topic explains how to determine the number of 4K records required for a member's checkpoint data set(s).
- "Placing a Checkpoint on a Coupling Facility for the First Time" on page 207
This topic describes how to start JES2 with a checkpoint data set residing on a coupling facility for the first time. Also, it contains guidance on how to correct errors in specifying the size of the coupling facility structure.
- "The Checkpoint Cycle" on page 208

This topic describes the stages through which JES2 reads and writes checkpoint records in a MAS environment. This data is especially helpful when using ID TRACE 17.

- “Checkpoint Configuration Modes” on page 212
This topic explains how you decide what mode to specify for your checkpoint data set(s) (DUPLEX with backup, DUPLEX without backup, or DUAL), using the MODE= and DUPLEX= subparameters on the CKPTDEF initialization statement.
- “Accessing the CKPTn Data Set in a MAS” on page 221
This topic describes how you can use the HOLD= and DORMANCY= parameters on the MASDEF initialization statement to control how access to the checkpoint is shared in a MAS environment.
- “Replacement Data Set (NEWCKPTn) Definition” on page 223
This topic describes how you can specify replacement checkpoint data set definitions to ease recovery when JES2 loses access to the CKPTn data set(s).
- “Checkpoint Reconfiguration, An Overview” on page 228
This topic describes how you can redefine the JES2 checkpoint data set configuration dynamically to replace, discontinue use, or resume using a checkpoint data set.
- “Recovering from Member Failures on Other JES2 Members” on page 245
This topic explains how you can use JES2 operator commands or the AUTOEMEM option to make jobs from a failed member eligible for restart on an active MAS member.
- “Providing Copies of the JES2 Checkpoint to Application Programs” on page 252
This topic explains how authorized application programs can obtain a copy of the checkpoint data set.

Placement of the Checkpoint Data Set

An installation can place checkpoint data set(s) (primary or secondary) on either a coupling facility structure, a DASD volume, or a combination of these locations. DASD used to hold checkpoint data sets can be all the same device type and model or any combination of JES2-supported (refer to “Appendix A. IBM Devices Supported by JES2 and How to Use Them” on page 379) device types and models.

Within a MAS, an installation can specify:

1. “Primary Checkpoint on a Coupling Facility Structure, Secondary Checkpoint on DASD”
2. “Both Checkpoints on DASD”

Primary Checkpoint on a Coupling Facility Structure, Secondary Checkpoint on DASD

Placing the primary checkpoint on a coupling facility structure provides more equitable access for all members of a MAS than that available through DASD because of the coupling facility lock. To ensure the security of that data through the DUPLEX copy retained on DASD, IBM recommends this placement for MAS configurations with four or more members.

Both Checkpoints on DASD

Placing both checkpoints on DASD volumes reduces throughput of data and can lock out smaller MAS members from access to the checkpoint. For information on tuning checkpoints residing on DASD, see “Controlling the Size of the Change Log” on page 200 and “Controlled Checkpoint Data Set Access” on page 221.

For further information concerning specification of checkpoint data sets, refer to the CKPT1= and CKPT2= initialization parameter descriptions on the CKPTDEF statement in *z/OS JES2 Initialization and Tuning Reference*.

Attention: IBM does not recommend placing both checkpoints on coupling facility structures or placing the primary checkpoint on DASD and the secondary checkpoint on a coupling facility structure. If both checkpoints reside on coupling facilities that become volatile (a condition where, if power to the coupling facility device is lost, the data is lost), your data is less secure than when a checkpoint data set resides on DASD. If no other active MAS member exists, you can lose all checkpoint data and require a JES2 cold start. Placing the primary checkpoint on DASD while the secondary checkpoint resides on a coupling facility provides no benefit to an installation.

Note: Note that all combinations of checkpoint data sets on DASD and coupling facility structures are supported as potential error recovery scenarios through the checkpoint reconfiguration dialog.

Benefits of Using a Coupling Facility

Placing a checkpoint on a coupling facility structure ensures equal access among MAS members and provides a better use of system resources than that available through DASD. Data can be transferred to and from a coupling facility much faster than to and from DASD.

JES2 uses the coupling facility lock to serialize access to the checkpoint data set. This coupling facility lock is better than the hardware RESERVE and RELEASE macros required for DASD because it ensures all members fair access to the checkpoint through first-in, first-out (FIFO) queuing. The coupling facility lock affects only the checkpoint data set, while the hardware RESERVE macro locks the entire volume upon which the DASD checkpoint resides.

Checkpoint Data Set Specifications

The following describes how to specify checkpoint data sets through the CKPTDEF initialization statement.

The CKPT1= specification is used for the primary data set copy of the JES2 checkpoint information, and the CKPT2= specification is used for either the DUPLEX data set copy (if operating in DUPLEX mode) or the second primary data set copy (if operating in DUAL mode). Before setting the DUPLEX=ONIOFF parameter for a particular member of your configuration, you should consider whether it is practical for your MAS to use an entire volume for the duplex data set.

If the checkpoint resides on DASD, prefix the checkpoint data set names with SYS1. to provide a complete data set name (for example, SYS1.JESCKPT1 and SYS1.JESCKPT2). Define the placement of these data sets using the VOLser subparameter of the CKPT1= and CKPT2= parameters on the CKPTDEF initialization statement.

If the checkpoint resides on a coupling facility structure, you do not specify a volume. In this manual, checkpoints that reside on coupling facility structures are represented as SYS1_CKPT1 and SYS1_CKPT2. Either the CKPT1= or the CKPT2= parameter on the CKPTDEF initialization statement must be specified; there is no default for the data set name, the volume serial number, or the structure name. Proper placement is vital to JES2 performance, particularly in a multi-access spool configuration environment.

“Part 7. Providing Security for JES2” on page 341 discusses using RACF to protect the checkpoint data sets that reside on DASD. Checkpoint data sets that reside on a coupling facility structure are RACF-protected by the coupling facility service.

CKPTn Data Set Definition and Placement on a Coupling Facility

Checkpoint data sets on a coupling facility structure are suitable for MAS configurations of all sizes (2- to 32-member). The coupling facility lock removes the need for both the software lock and the hardware RESERVE and RELEASE logic. JES2 use of the coupling facility lock provides for more equitable sharing of the checkpoint among all members. On DASD, a faster processor can monopolize a processor's shorter channel path to the checkpoint. When the checkpoint resides on a coupling facility, the first-in, first-out (FIFO) method of queuing ensures that all MAS members can have equal access to the data.

To place a JES2 checkpoint data set on a coupling facility structure, you must first define that structure in your installations' administrative coupling facility resource management (CFRM) policy. Once an installation activates an administrative policy, it becomes the active policy. For more information about installing a coupling facility, see *z/OS MVS Setting Up a Sysplex*. Specify the coupling facility structure's name through the STRNAME= subparameter of the CKPT1= and CKPT2= parameters on the CKPTDEF initialization statement.

Recommendation for Initializing a Checkpoint on a Coupling Facility Structure

IBM recommends initializing JES2 with the checkpoint data sets defined on DASD, and then forwarding them to a previously-defined coupling facility through the checkpoint reconfiguration dialog. For more information about how to perform this task, see both “Replacement Data Set (NEWCKPTn) Definition” on page 223 and “Checkpoint Reconfiguration, An Overview” on page 228.

Note: When JES2 connects to the specified coupling facility structure, RACF protection is provided.

Ensuring the Integrity of Checkpoint Data

Through the VOLATILE= parameter, JES2 allows you to specify how an installation responds when a coupling facility with a checkpoint data set structure becomes volatile. Note that a coupling facility is always considered volatile unless you have taken measures to protect against the loss of power to that coupling facility. Refer to *ES/9000 and ES/3090 PR/SM Planning Guide* for a description of how to monitor the volatility of coupling facilities.

When a coupling facility becomes volatile, if power to the coupling facility is lost, all data on the coupling facility structure is lost; JES2 cannot guarantee the integrity of the data. If you do not specify this parameter, it defaults to WTOR for both the ALLCKPT= and the ONECKPT= subparameters.

Note: When a volatile coupling facility becomes non-volatile, JES2 does not inform you of the change. Use the \$D CKPTDEF command to monitor the volatile status of your checkpoints.

There are two values for VOLATILE=

- **ONECKPT** - Used by JES2 when another available (INUSE=YES) checkpoint is still non-volatile.
- **ALLCKPT** - Used by JES2 when all available (INUSE=YES) checkpoints are volatile.

Ignoring the Volatile Status: If you have a primary checkpoint data set residing on a coupling facility and a secondary checkpoint data set residing on DASD, you can specify:

```
CKPTDEF .... VOLATILE=(ONECKPT=IGNORE)
```

If the one structure becomes volatile, JES2 ignores the status change; the member issues no message and does not force an operator into the checkpoint reconfiguration dialog. In this instance, you might want to specify IGNORE for ONECKPT= because the secondary checkpoint data set ensures the integrity of your installation's data. Because DASD data sets are always non-volatile, the ALLCKPT setting has no effect in this configuration.

Requesting Operator Intervention for Volatile Status: If both checkpoints reside on different coupling facilities, you can be notified when both checkpoints become unstable. You can specify:

```
CKPTDEF .... VOLATILE=(ONECKPT=IGNORE,ALLCKPT=WTOR)
```

WTOR ensures that JES2 sends a message to the operator console. You can choose to run with an unstable checkpoint or enter the checkpoint reconfiguration dialog to change the primary checkpoint data set. Because ONECKPT=IGNORE, JES2 issues this message only when both coupling facilities become volatile (unstable). This is the state where, if power to the coupling facility is lost, all data on the coupling facility is lost. However, if both checkpoints have been specified as coupling facility structures, but the secondary checkpoint specifies INUSE=NO, JES2 uses the ALLCKPT specification, because the primary checkpoint data set is the only available checkpoint.

For JES2 to issue a message when only one of the checkpoint data sets becomes volatile, specify

```
CKPTDEF .... VOLATILE=(ONECKPT=WTOR,ALLCKPT=WTOR)
```

If either or both checkpoints become volatile, JES2 issues the message that allows you to decide whether to enter the checkpoint reconfiguration dialog or continue processing without making a change. Because it is important to monitor the status of the checkpoint, the VOLATILE= parameter defaults to WTOR for both the ONECKPT and ALLCKPT subparameters.

Requesting Immediate Invocation of Dialog: If you would rather enter the checkpoint reconfiguration dialog as soon as a coupling facility becomes volatile, you can specify:

```
CKPTDEF .... VOLATILE=(ONECKPT=DIALOG,ALLCKPT=DIALOG)
```

For more information about using the checkpoint dialog to **forward** checkpoint specifications, see "Checkpoint Reconfiguration, An Overview" on page 228.

CKPTn Data Set Definition and Placement on DASD

Checkpoint data sets should reside on a high-speed, low-usage device, and they should be allocated on a cylinder boundary. If available, the best location for each data set is on a dedicated 3390 device. To obtain optimum performance, the CKPT1 and CKPT2 data sets should be the only data sets on their respective DASD volumes if your configuration is operating in DUAL checkpointing mode. If your configuration is operating in DUPLEX mode, the data set defined by the CKPT1= parameter should reside on a separate volume. (Refer to "Checkpoint Configuration Modes" on page 212 for an explanation of DUAL and DUPLEX modes.)

IBM recommends placing the CKPTn data sets on separate volumes to ease recovery. If the CKPTn data sets are physically removed from one another, they have separate power sources, separate control units, and no single common point of failure.

Note: All members of a MAS configuration must have at least one channel path to the device containing the primary checkpoint data set(s).

Figure 36 provides an example for defining checkpoint data sets.

```
//ALLOCATE JOB (...),'PREPARE FOR JES2',MSGLEVEL=1
//ALLOCAT EXEC PGM=IEFBR14
//*
:
//*
//CHECK1 DD DSN=SYS1.JESCKPT1,UNIT=3390,
//          VOLUME=SER=CHECK1,DISP=(NEW,KEEP),
//          SPACE=(ABSTR,(45,15)),DCB=(DSORG=PSU)
//*
//CHECK2 DD DSN=SYS1.JESCKPT2,UNIT=3390,
//          VOLUME=SER=CHECK2,DISP=(NEW,KEEP),
//          SPACE=(TRK,13256),DCB=(DSORG=PSU)
/*
```

Figure 36. Example of Defining Checkpoint Data Set

Performance can be severely degraded if the checkpoint data set(s) resides on a SPOOL volume; avoid placing a checkpoint data set on a SYS1.HASPACE data set.

If you use global resource serialization, it is strongly recommended that you add the checkpoint data set(s) to the member exclusion resource name list (RNL). If you do, global resource serialization does not delay a JES2 member's access to the data sets checkpoint data sets. Refer to *z/OS MVS Planning: Global Resource Serialization* for further information on this procedure.

Attention: Do not use a hardware RESERVE to serialize access to any other data set on the CKPT1 or CKPT2 volumes. If you do, serious degradation of JES2 throughput or a deadlock situation can result.

Controlling the Size of the Change Log

When the checkpoint data set resides on DASD, the change log communicates checkpoint updates to the member that is reading the checkpoint. Because the change log only communicates the changes to the 4K records (not each entire 4K record that has a change recorded on it), checkpoint performance is enhanced. If the change log is small, it will reside only on the first track of the checkpoint data set. This is desirable because it can then be read at the same time as the Lock, Check, and Master Records during the initial (READ1) portion of the checkpoint cycle thereby decreasing the amount of I/O to the checkpoint. If the used portion of the change log is large and spills onto the second track, a second read is required.

You can use the LOGSIZE= parameter on the CKPTDEF initialization statement to control the size of the change log. If you do not assign a value to that parameter, JES2 calculates a value based on the checkpoint mode (DUPLEX vs DUAL; for more information on the modes, see "Checkpoint Configuration Modes" on page 212) and the number of change log records that fit on track 1 of the checkpoint data set defined by CKPT1= and CKPT2= on the CKPTDEF statement. (Refer to the LOGSIZE= parameter on the CKPTDEF statement for the specific

algorithm used to calculate the default change log size.) The LOGSIZE= value can be changed either on a cold start or an all-member warm start.

Storage Management Considerations on DASD

Be careful when using an automated storage management tool on a volume that contains the JES2 checkpoint. Because MVS does not record that JES2 allocated the checkpoint data set, the tool could attempt to move the data set erroneously.

Do not allow any automated storage management tool to move the JES2 checkpoint data set while the JES2 that uses it is active. You **must** inform the tool not to move the checkpoint data set by specifying DCB=(DSORG=PSU) on the DD JCL statement that allocates the checkpoint data set. However, this method might not work with all products.

Determining the Size of Your Checkpoint Data Set

Adequately determining the size of your checkpoint data set is critical to JES2's ability to initialize, and it should be large enough for future expansion. This section presents it as a 2-step procedure:

Step 1: Determine the number of 4K records needed to contain the checkpoint.

Step 2: Use the 4K value to determine the number of cylinders for DASD or kilobytes for a structure size.

If you don't want to calculate the size, you can use a trial-and-error approach by over-allocating the space (two or three times your current allocation) and let JES2 tell you with the \$HASP296 or \$HASP542 message if you need more. The largest checkpoint that JES2 will currently use is approximately 1010 tracks on a 3390 device (Approximately 12,120 4k records). Allocating a new data set of this size will ensure that it can accommodate increasing any section to the maximum size.

Determining the Current Checkpoint Size

The \$HASP537 message at JES2 initialization displays the number of 4K records in your checkpoint. However, this number will not allow for any increase to these parameters.

Use the \$D CKPTSPACE command to determine the size of the checkpoint and amount of free space in the current checkpoints.

Determining the New Checkpoint Size

The \$HASP537 message at JES2 initialization displays the number of 4K records needed for the checkpoint data set. This number does not allow for any increase to these parameters nor for expansion by the \$ACTIVATE command which is necessary to enable new functions at the current JES2 level.

To determine how much checkpoint space to allocate to allow the \$ACTIVATE command you can issue \$DACTIVATE and the response will display the number of 4K pages needed.

To determine how much checkpoint space to allocate for a new release or for expansion:

1. Cold start a secondary JES2 specifying the maximum values to be supported for the specifications identified in Table 50 on page 202. You should use values for the specifications that reflect what you might need in the future. If you want

values for an unactivated system be sure to specify PARM=UNACT since otherwise COLD start assumes you will be activated.

2. The HASP537 message will display the number of 4K records required for the checkpoint data set.

Table 50. JES2 Parameters Affecting Checkpoint Size

Description	Initialization Parameter	Default
Number of Spool Volumes	SPOOLDEF SPOOLNUM=	32
Number of Track Groups on Spool	SPOOLDEF TGSPACE=(MAX=)	16288
Size of Job Queue	JOBDEF JOBNUM=	1000
Range of JOBIDs	JOBDEF RANGE=	1–9999
Size of Job Output Queue	OUTDEF JOENUM=	2.5 x JOBNUM
Size of Change Log on Checkpoint	CKPTDEF LOGSIZE=	1 (if MODE=DUPLEX) 1 to 9 (if MODE=DUAL)
Size of Block Extension Reuse Table	CKPTSPACE BERTNUM=	2 x JOBNUM + 100

If you wish to overallocate checkpoint for expansion but do not want to determine specific values, consider allocating 2 to 3 times your current checkpoint space.

If you need more space, you can use the checkpoint reconfiguration dialog to move the checkpoints to larger data sets or structures.

Use the \$D CKPTSPACE command to determine the size of the checkpoint and amount of free space in the current checkpoints. Use the \$D ACTIVATE command to see if \$ACTIVATE has been issued.

Allow Room for Dynamic Checkpoint Expansion

You should use values in the following calculations that reflect what you might need in the future. The CKPTSPACE BERTNUM parameter defines how much additional space is available for expanding the JES2 checkpoint record. The default value is based on the number of jobs defined by the JOBDEF JOBNUM parameter.

If you need more space, you can use the checkpoint reconfiguration dialog to move the checkpoints to larger data sets or structures. You can also increase the amount of space reserved for expansion with the \$T CKPTSPACE BERTNUM= command.

Step 1: Calculating 4K Records

The size requirements for the JES2 checkpoint data is based on the values you assign to the following initialization parameters:

Table 51. JES2 Parameters Affecting Checkpoint Size

Description	Initialization Parameter	Default Value
Number of Spool Volumes	SPOOLDEF SPOOLNUM=	32
Number of Track Groups on Spool	SPOOLDEF TGSPACE=(MAX=	16288
Size of Job Queue	JOBDEF JOBNUM=	1000
Size of Job Output Queue	OUTDEF JOENUM=	2.5 x JOBNUM

Table 51. JES2 Parameters Affecting Checkpoint Size (continued)

Description	Initialization Parameter	Default Value
Size of Change Log on Checkpoint	CKPTDEF LOGSIZE=	1 (if MODE=DUPLEX) 1 to 9 (MODE=DUAL)
Size of Block Extension Reuse Table (BERT)	CKPTSPACE BERTNUM=	2 x JOBNUM + 100

Using these parameter values you can calculate how much space you need on DASD or in a coupling facility structure for your JES2 checkpoint data sets.

Calculating the Number of 4K Records Needed

Use the following table to determine the number of 4K records needed for each of your checkpoints.

Table 52. Total 4K Records for the JES2 Checkpoint

Checkpoint Information	Formula (size calculation) or Assumption (Round all fractions up to the next integer)	Number of 4K Records
Fixed	Master, SCQ, JIX, RSO, LCK, DAS, Misc.	85
Change Log	CKPTDEF LOGSIZE =	
Track Group	(SPOOLDEF TGSPACE=MAX=) / 16288	
Job Queue (JQEs, JQX)	(JOBDEF JOBNUM=) / 31 + (JOBNUM x (SPOOLDEF SPOOLNUM=)) / 32K	
Output Queues	(OUTDEF JOENUM=) / 37	
Expansion Blocks (BERTs)	(CKPTSPACE BERTNUM=nnnnnn) / 64	
Track 1 Correction	# of 4K records per track (see Table 54 on page 204)	
Total		

Sample Calculation

To illustrate how to calculate the exact size of the checkpoint, Table 53 on page 203 provides an example based on the following JES2 initialization parameters:

```
CKPTDEF LOGSIZE=8
SPOOLDEF SPOOLNUM=32
SPOOLDEF TGSPACE=(MAX=97728)
JOBDEF JOBNUM=2000
OUTDEF JOENUM=5000
CKPTSPACE not specified (BERTNUM defaults to 2 * JOBNUM + 100)
```

Table 53. Sample Checkpoint Size Calculation

Checkpoint Information	Formula (size calculation) or Assumption (Round all fractions up to the next integer)	Number of 4K Records
Fixed	Master, SCQ, JIX, RSO, LCK, DAS, Misc.	85
Change Log	8	8
Track Group	97728 / 16288	6
Job Queue	2000 / 31 + 2000 x 32 / 32K = 65 + 2	67
Output Queues	5000 / 37	136
Expansion Blocks	((2 x 2000) + 100) / 64	65
Track 1 Correction	3380 Device	10

Table 53. Sample Checkpoint Size Calculation (continued)

Checkpoint Information	Formula (size calculation) or Assumption (Round all fractions up to the next integer)	Number of 4K Records
Track 1 Correction	3390 Device	12
Total	3380 Device	376
Total	3390 Device	378

Step 2: Calculating the Checkpoint Size

Once you determine the number of 4K (4096 byte) records, you should add 5 to the number to allow for the possible unused track 0 space. Then use this number as described in Table 54 (Number of 4K Records per Track and Cylinder for Various DASD Devices) to determine the number of cylinders on DASD. To determine the size of the structure required for checkpoint on a coupling facility use Figure 37 on page 206 or the coupling facility wizard on the world wide web (<http://www.s390.ibm.com/cfsizer/jes.html>). The number of cylinders on DASD or size of the structure in the coupling facility must be sufficient or JES2 will not initialize.

Remember you should define two checkpoints (CKPT1 and CKPT2) as well as back-up checkpoints (NEWCKPT1 and NEWCKPT2). The previous calculations provided the size of the checkpoint, and each data set or structure is allocated individually.

Don't forget to allow for extra space for dynamic checkpoint expansion.

Specifying the Storage of Checkpoints on DASD

Once you have calculated the number of 4K records for the checkpoint "Step 1: Calculating 4K Records" on page 202, use Table 54 to determine the number of tracks or cylinders on DASD, and round up to the nearest whole number.

Table 54. Number of 4K Records per Track and Cylinder for Various DASD Devices

DASD Device Type	3380	3390	9340
# of 4K Records per Track	10	12	10
# of 4K Records per Cylinder	150	180	150

Notes:

1. Track 1 contains only the Check, Lock, and Master records, plus as many change log records (4K each) that will fit on the remainder of the track. Track 1 correction is needed (see Table 52 on page 203 and Table 53 on page 203) because track 1 is usually not filled to capacity.
2. The change log records can overflow onto subsequent tracks.
3. If the data set is not large enough, JES2 issues the \$HASP296 message to indicate the number of additional tracks required. (There is no penalty for over-estimating the number.)

In Table 53 on page 203, 426 4K records require the following amount of space on 3380 or 3390:

3380: 38 tracks ($376 / 10 = 37.6$), or 3 cylinders ($376 / 150 = 2.5$)

3390: 32 tracks ($378 / 12 = 31.5$), or 3 cylinders ($378 / 180 = 2.1$).

Syntax for Checkpoint Space Allocation on DASD

Once you have the number of tracks or cylinders required for the checkpoint, you can use the JCL SPACE= parameter to define the size of the checkpoint on a particular volume. Table 55 presents an example of DASD checkpoint data set definition and allocation. Following the example is the syntax for the JCL SPACE= parameter.

Table 55. Example of Defining and Allocating DASD JES2 Checkpoint Data Sets

```
//ALLOCATE JOB (...),'PREPARE FOR JES2',MSGLEVEL=1
//ALLOCAT EXEC PGM=IEFBR14
//*
//CHECK1 DD DSN=SYS1.JESCKPT1,UNIT=3390,
//          VOLUME=SER=CHECK1,DISP=(NEW,KEEP),
//          SPACE=(ABSTR,(45,15))
//*
//CHECK2 DD DSN=SYS1.JESCKPT2,UNIT=3390,
//          VOLUME=SER=CHECK2,DISP=(NEW,KEEP),
//          SPACE=(ABSTR,(45,15))
/*
```

Note: These data sets are defined on the CKPTDEF initialization statement with the DSName=, and VOLser= subparameters on the CKPT1= and CKPT2= parameters, respectively.

The checkpoint data set should be allocated as a single extent starting on a cylinder boundary. JES2 will use only the first extent. Specify space allocation for the checkpoint data set either in absolute tracks (ABSTR) or cylinders (CYL) as follows:

►►SPACE=—(—ABSTR,(primary-qty,address)—)—————►
 └(—CYL,primary-qty—)—————┘

SPACE

specifies the amount of space needed for a new data set on a direct access volume.

ABSTR

specifies that the data set is to be placed at a specific location on the volume. Be certain this location is at the start of a cylinder boundary. ABSTR is recommended if you do not intend to dedicate an entire volume to the checkpoint data set.

CYL

specifies that the data set is to be allocated in cylinders. The CYL specification is available as an alternative method of allocating space for those installations that dedicate an entire volume to the checkpoint data set.

primary-qty

- For ABSTR - specifies the number of full tracks to be allocated
- For CYL - specifies the number of full cylinders to be allocated

address

specifies the track number of the first track to be allocated

Specifying the Storage of Checkpoints on Coupling Facility Structures

When the checkpoint resides on a coupling facility structure, the checkpoint data set requires additional storage for that structure. JES2 uses a list structure for its checkpoint data set structure. Approximately 85% of the structure can reside in non-control storage (expanded storage).

Approximate Storage Requirements on Coupling Facility Structures

Once you have calculated the number of 4K records from “Step 1: Calculating 4K Records” on page 202, you can calculate the structure requirement by the formula:

$$(\text{\# of 4K records}) \times 4.4 \text{ (round up to 256K increment)} + 256\text{K}$$

Figure 37. Estimated Structure Sizes for JES2 Checkpoint on a Coupling Facility

Specify the size of the JES2 structure in your installation's active Coupling Facility Resource Management (CFRM) policy as described in *z/OS MVS Setting Up a Sysplex*.

Notes:

1. Allocation is in 256K increments.
2. The Check record requires 4K bytes.
3. The Lock record is not written.
4. The Master record is broken into 4K segments.
5. There is no Change Log on a coupling facility.
6. If the structure size is not large enough, JES2 issues the \$HASP542 error message to indicate the number of additional 4K records required. (There is no penalty for over-estimating the number.)

In Table 53 on page 203, 426 4K records require **2304**-kilobytes for a coupling facility structure. Use the number 2304 as the maximum list-set-entry count.

Detailed Storage Requirements on Coupling Facility Structures

If you want more precise calculations for the size of the coupling facility structure, you can use the formula for determining the size of a serialized list structure in *ES/9000 and ES/3090 PR/SM Planning Guide*.

A structure intended for use as a JES2 checkpoint data set requires the following attributes:

- List-structure-type with names but neither keys nor adjuncts.
- Target entry-to-element ratio value of 1
- List-element-characteristic value of 4
- Maximum data-list-entry size value of 1
- Lock-table-entry characteristic value of 0
- Lock-table-entry count value of 2
- List count value of 2
- Maximum list-set-entry count derived from the number of 4K records determined through either the \$HASP537 message or the JES2 checkpoint data set formula.

Placing a Checkpoint on a Coupling Facility for the First Time

When placing a checkpoint data set on a coupling facility structure for the first time, IBM recommends defining the JES2 checkpoint on a secondary JES2 (preferably a test system). Starting the checkpoint on a secondary JES2 ensures connectivity to the coupling facility and allows you to verify the accuracy of the coupling facility resource management (CFRM) policy definition. Then you can use the checkpoint reconfiguration dialog to forward the primary JES2 member's checkpoint data set onto the coupling facility structure. To start a JES2 member with a checkpoint data set residing on a coupling facility structure for the first time, use the following procedures:

1. Ensure that you have followed the instructions for predefining a coupling facility resource management (CFRM) policy as described in “Defining JES2 Structures in a CFRM Policy” on page 11.
2. Start a primary JES2 member as described in “Starting JES2 for the First Time (A Cold Start)” on page 36.

Note the number of 4K records specified on the \$HASP537.

3. Cold start a secondary JES2 member with the checkpoint defined on a coupling facility structure, using the STRNAME= subparameter instead of the DSNAME= and VOLSER= subparameters on the CKPTDEF initialization statement. Follow the directions provided in “Defining a Secondary JES2 Member to MVS” on page 51.

Ensure that the secondary member's JES2 definitions match those of the primary JES2 member for the following initialization parameters that define the checkpoint data set:

- SPOOLNUM= and TGSPACE=(MAX=) on the SPOOLDEF initialization statement
 - JOBNUM= on the JOBDEF initialization statement
 - JOENUM= on the OUTDEF initialization statement
 - BERTNUM= on the CKPTSPACE initialization statement.
4. If problems occur when initializing the JES2 secondary, see both “Correcting a Structure Error of Size” and “Correcting a Structure Error of Incorrect Attributes” on page 208.
 5. Once JES2 is fully operational (after you receive the \$HASP400 message), verify that the coupling facility structure has been allocated by using the \$D CKPTDEF command to display the status of all defined JES2 checkpoint data sets.
 6. After you have completed testing the checkpoint on a coupling facility, bring down the secondary JES2 member and invoke the JES2 reconfiguration dialog through operator command to forward the checkpoint data set to the coupling facility.

For complete instructions on how to use the checkpoint reconfiguration dialog, see “Operator-initiated Entrance into a Checkpoint Reconfiguration Dialog” on page 238.

Correcting a Structure Error of Size

During initialization, JES2 issues the following messages if the size of the coupling facility structure is too small to contain the checkpoint data set:

- The \$HASP536 message with the following error message:

08, STRUCTURE IS NOT LARGE ENOUGH

- The \$HASP542 message with the following text:

HASP542 MEMBER *member_name*--STRUCTURE*strname*
IS NOT LARGE ENOUGH TO CONTAIN ALL CHECKPOINT DATA.
THE CURRENT SIZE IS *cccccc*K. THE SIZE MUST BE INCREASED
TO HOLD AN ADDITIONAL *nnnnnn* 4K ELEMENTS. THIS WOULD
REQUIRE A STRUCTURE SIZE OF AT LEAST *mmmmmm*K.

When you receive this message sequence, you must do one of the following tasks in order of preference (the first being easiest and most preferable):

1. If you have a predefined structure of adequate size to contain the JES2 checkpoint data set in a CFRM policy, you can activate that structure through the STRNAME= value on the CKPTDEF initialization statement.
2. If you do not have a predefined structure of adequate size in any CFRM policy, run the MVS utility cited in “Defining JES2 Structures in a CFRM Policy” on page 11 and define a structure in a CFRM policy before continuing JES2 initialization.

Then, use the SETXCF commands to specify a new active CFRM policy that contains a predefined structure with enough 4K records to contain the checkpoint.

3. If you cannot run the MVS utility to create a CFRM policy, invoke the initialization version of the checkpoint reconfiguration dialog and specify the checkpoint data sets on DASD.

Note: For more information about how to use the SETXCF commands in specific scenarios, see *z/OS MVS System Commands*.

Correcting a Structure Error of Incorrect Attributes

During initialization, JES2 issues the \$HASP536 message with return codes 1 through 7 if a structure intended to hold a JES2 checkpoint contains the wrong attributes. In this case, ensure that you have specified the correct STRNAME on the CKPTDEF initialization statement. If you have, use the SETXCF commands to disconnect from the structure and then RESPECIFY the same structure during initialization. Respecifying the same STRNAME allows you to change the attributes of the original structure. See *z/OS MVS Programming: Sysplex Services Guide* for more information on coupling facility structure attributes.

If this does not work, you might have to specify DASD values for the checkpoint data set through the initialization version of the checkpoint reconfiguration dialog.

The Checkpoint Cycle

Although the actual checkpoint cycle consists of a number of reads and writes, it can be considered to include only four basic phases. Depending on whether your complex is processing in DUPLEX mode or DUAL mode (see “Checkpoint Configuration Modes” on page 212), the actual specifics of the checkpoint process will vary somewhat; however, the basic processing is as follows:

1. Gaining checkpoint control (and RESERVE for DASD)
2. Owning the checkpoint to read and make updates
3. Final writing (and RELEASE for DASD)
4. Allowing other members access opportunity

As you read the following description of the checkpoint cycle, refer to Figure 38 on page 209, which represents a 3-member multi-access spool configuration.




Figure 38. The Checkpoint Cycle (In a 3-Member Multi-Access Spool Environment)

Checkpoint Cycle Overview

If a checkpoint data set resides on a coupling facility structure, serializing access to the checkpoint is greatly simplified because the coupling facility uses its own lock. As a result, checkpoint data sets residing on a coupling facility do not use RESERVE/RELEASE logic or the JES2 software checkpoint lock. Placing the checkpoint data sets on a coupling facility structure reduces the amount of dormant (non-useful) time in the checkpoint cycle.

When a checkpoint data set resides on DASD, JES2 obtains exclusive ownership of the checkpoint data set with a RESERVE (using the MVS RESERVE macro). The RESERVE is always issued against the data set defined by CKPT1=, unless that data set is inactive. If CKPT1 is inactive, the RESERVE is issued against the data set defined by CKPT2=. No other member is allowed access to the checkpoint data

set until the member performing the update issues a RELEASE (using the MVS DEQ macro) for the volume on which the data set resides.

To detect and avoid problems due to the early release of the hardware lock initiated by the RESERVE, JES2 uses a backup software checkpoint lock for the checkpoint data set. The checkpoint lock is the first record on the first track of each data set. When a member has control of the primary checkpoint data set, it writes a member-dependent value into the key and data portions of the checkpoint lock record. Therefore, even if the RESERVE fails, other members in the multi-access spool configuration that try to access the checkpoint data set are prevented from doing so by the checkpoint lock.

If the member holding the checkpoint lock fails before releasing the lock, it prevents other members from checkpoint data set access. Then JES2 issues the following message:

```
$HASP264 WAITING FOR RELEASE OF CHECKPOINT LOCK [BY membername]
```

If the checkpoint resides on DASD and the member holding the checkpoint lock fails before releasing the lock, use the \$E CKPTLOCK,HELDDBY= command to reset the lock and allow access to the checkpoint data set by the next member requiring checkpoint data set information. Before you reset the checkpoint lock, ensure that the member currently holding the checkpoint lock has failed. If you have enabled the AUTOEMEM option, JES2 requeues failed jobs for processing within the sysplex.

If the checkpoint resides on a coupling facility and the member holding the coupling facility lock fails before releasing the lock, the \$HASP263 message is informational; wait for the MVS system to release the coupling facility lock. Then you can issue the \$E MEMBER operator command or use the AUTOEMEM option to requeue the failed member's jobs on an active member. To use the AUTOEMEM option, see "Recovering from Member Failures on Other JES2 Members" on page 245.

Phase I - Checkpoint RESERVE, Lock, and Read

Once a particular member obtains the checkpoint lock (whether the JES2 software lock or the coupling facility lock), that member can access the checkpoint data.

The JES2 member:

1. Reads the first track of the checkpoint data set (**READ1**).
2. Reads the updated 4K records (**READ2**).

If the data set resides on DASD and MODE=DUAL, JES2 could have to read in the remainder of the change log if it has spilled onto track 2. The size of the change log that must be read is, of course, dependent upon the number of changed control blocks that reside there.

Also, in DUAL mode, if more than one checkpoint cycle has taken place since the previous access (by this member), additional 4K records might have to be read.

3. Merges changes into the in-storage copy of the checkpoint before setting the HOLD time.

This task must be completed before useful work requiring the checkpoint can begin.

Phase II - Updating the Checkpoint

When a member has read the checkpoint data set, it can update its in-storage copy of its job and output queues. The changes are recorded on either DASD or the coupling facility by a series of writes: the primary write, intermediate write(s), and the final write. These writes allow the member holding the lock to update checkpoint data to reflect its “view” of member activity.

1. The **primary write** updates the 4K records of the checkpoint data set that is not the most current. These 4K records are located after the first track of the checkpoint data set.

If the checkpoint data set resides on DASD, these 4K records follow the change log if the change log ends on track 1. If, however, the change log is contained on a subsequent track(s), the 4K records are located on that track immediately following the change log.

If the checkpoint data set resides on a coupling facility, there is no change log.

2. The **intermediate writes** record all changes a member makes to the checkpoint data.

If the checkpoint data set runs in DUAL mode, JES2 records these changes in the change log.

If the checkpoint data set is in DUPLEX mode, JES2 records these changes in the 4K records of the data set.

In either case, these changes are read during the next member’s phase I; that member’s in-storage copy is updated to reflect the current status. During the ownership period, the owning member can make updates to the checkpoint data. Intermediate versions of the checkpoint information are written without losing checkpoint control.

In DUAL mode, the MAS configuration operates with two primary checkpoint data sets:

- The most recently updated data set
- The “down-level” data set.

The down-level data set holds checkpoint information that is one checkpoint cycle behind. This down-level data set was read from, but not written to (updated), during the last checkpoint cycle. In both modes of operation (DUAL and DUPLEX), the first write (that is, the primary write) is always to the down-level data set in order to bring it up to date.

If one member holds the checkpoint a sufficient length of time to have done 10 intermediate writes, the down-level data set is updated following the tenth intermediate write.

Phase III - Final Checkpoint Write and Data Set Release

The member does a **final write** just prior to releasing the checkpoint lock. If the checkpoint resides on DASD, when this final write is completed the member holding the RESERVE issues a DEQ, and other members are able to access the newly-updated information. If the checkpoint resides on a coupling facility, when this final write is completed, the coupling facility lock releases the checkpoint.

Phase IV - Other Member Access

Based on the specifications you assigned to the DORMANCY= parameter on the MASDEF statement, the member that just had checkpoint access will not be allowed access for a period of time. This dormant period allows other members a time of “non-contended” access. Minimally, to assure access of the checkpoint by other members, DORMANCY= should be set to a value not less than the sum of the HOLD= specifications for all other members. Refer to “Member-Specific Parameter Recommendations” on page 222 for performance recommendations for setting this parameter.

Checkpoint Configuration Modes

There are three ways of specifying the checkpoint configuration mode for your JES2 checkpoint configuration:

- “DUPLEX-Mode Processing (With Backup)”
- “DUPLEX-Mode Processing (Without Backup)” on page 216
- “DUAL-Mode Processing” on page 217.

The type of mode you select depends upon your JES2 configuration. For example, if a checkpoint data set resides on a coupling facility structure, the mode must be DUPLEX. If an installation specifies MODE=DUAL on the CKPTDEF initialization statement, JES2 processing forces the mode to DUPLEX and notifies the operator through an informational message.

The following examines performance considerations and explains:

- How to initialize your member to process in a selected mode
- Recommendations on what mode is most appropriate for your member configuration
- Recovery procedures available in the event of an ABEND, I/O error, or hardware problem

DUPLEX-Mode Processing (With Backup)

JES2 can operate its checkpoint configuration in DUPLEX mode if you have defined two checkpoint data sets, a primary and a duplex.

All members of your JES2 configuration (whether a single member operating in a single-member environment or multiple members operating as part of a multi-access spool configuration), should, if possible, operate with DUPLEX=ON on the CKPTDEF statement. This provides the greatest protection from checkpoint error.

DUPLEX (With Backup) on DASD

The primary data set is specified by the CKPT1= parameter on the CKPTDEF initialization statement and the duplex (secondary) data set is specified by the CKPT2= parameter on that same statement:

```
CKPTDEF CKPT1=(DSN=dsname,VOL=volser,INUSE=YES),
        CKPT2=(DSN=dsname,VOL=volser,INUSE=YES),
        MODE=DUPLEX,DUPLEX=ON
```

There is no requirement that these two data sets be on unique volumes; however, for performance reasons, and increased recovery potential, it is strongly recommended that you place them on separate volumes.

DUPLEX (With Backup) on Coupling Facility

If you define both checkpoint data sets on different structures within different Coupling Facilities, performance should be increased significantly. The primary data set is specified by the CKPT1= parameter on the CKPTDEF initialization statement and the duplex data set is specified by the CKPT2= parameter on that same statement:

```
CKPTDEF CKPT1=(STRNAME=strname, INUSE=YES),  
        CKPT2=(STRNAME=strname, INUSE=YES),  
        MODE=DUPLEX, DUPLEX=ON
```

The CKPT1 data set is the primary data set, that is, it is read from and written to at every intermediate read and final write of the checkpoint by all members in your multi-access spool configuration. The duplex data set, CKPT2, is updated less frequently (that is, once for every 10 writes to the primary). If the primary data set suffers an error, the duplex can provide either an exact duplicate of the primary or a very similar, almost current (depending on when it was last updated) copy, of the checkpoint data.

Figure 39 on page 214 and Figure 40 on page 215 provide diagrammatic views of this processing. Refer to these figures as you read the following example of duplex processing. Assume a 2-member multi-access spool configuration: members JESA and JESB, the primary checkpoint named CKPT1 and duplex named CKPT2.

A If JESA gains control of the checkpoint (Figure 39 on page 214), it reads from CKPT1 and

B Does the **primary write** to CKPT2.

C **Intermediate writes** are to CKPT1 with every tenth write (if there are 10 or more) also written to CKPT2.

D The **final checkpoint write** (prior to JESA releasing its RESERVE) is to CKPT1.

Note that if the checkpoint data set resides on a coupling facility structure rather than on a DASD volume, JESA access to the checkpoint is serialized through the coupling facility lock; the hardware RESERVE is not obtained or released.




Figure 39. Checkpoint Data Set Processing, DUPLEX Mode, Two-Member Multi-Access Spool Configuration - JESA Cycle

JESB now gains checkpoint control (Figure 40 on page 215);

- E** It, too, reads from CKPT1, and
- F** Performs the primary write to CKPT2.
- G** Intermediate writes are to CKPT1 with every tenth write to CKPT2, and
- H** SYSB's final write is to CKPT1.

This process continues, unless an error occurs, at which time you can dynamically reconfigure (forward, suspend, or resume use of the checkpoint data sets) your checkpoint data set specification by responding appropriately to checkpoint

reconfiguration dialog messages. (Refer to “Checkpoint Reconfiguration, An Overview” on page 228 for an explanation of these procedures.)




Figure 40. Checkpoint Data Set Processing, DUPLEX Mode, Two-Member Multi-Access Spool Configuration - JESB Cycle

Even if the primary checkpoint data set, CKPT1, is updated every checkpoint cycle, and the duplex, CKPT2, is updated on a regular basis, when an error occurs on the primary checkpoint data set, a more current copy of the checkpoint might be available to the member that experienced the error.

Each member holds an “in-storage” copy of the checkpoint, which it uses to update the checkpoint. This in-storage data set can be copied into the “replacement checkpoint”, NEWCKPTn, data set if one has been predefined (by initialization statement), or dynamically added (by operator command), or in response to

checkpoint reconfiguration dialog messages. However, if the member holding this up-to-date in-storage copy has also suffered a failure, the most up-to-date copy of the checkpoint available would be defined by the duplex checkpoint data set.

Note: DUPLEX mode checkpoint processing is recommended for single member configurations and required if any checkpoint data set resides on a coupling facility structure.

DUPLEX-Mode Processing (Without Backup)

You can specify that your member operate with a single checkpoint data set. In most cases, this mode is not recommended. Effectively, you are processing in an environment in which there will be no backup copy of the checkpoint data set. As a result, JES2 will not need to read/write to two data sets. If that data set becomes damaged, lost, or suffers an I/O error, and your member experiences a concurrent failure, you will have no checkpoint data set available to restart JES2.

However, depending on your specific volume or structure use and configuration, it might not be practical for particular members of your JES2 configuration to maintain a backup checkpoint. For example, a 32-way MAS could be composed of two 3090 processors that manage a heavy batch workload and 30 smaller processors that manage on-line transaction programs. To reduce the cost of storage overhead, this installation might run without a backup checkpoint on the 30 smaller processors, while ensuring that the 3090s operate with DUPLEX=YES.

Another scenario could involve a MAS composed of different level processors. An installation can determine that it is not efficient to run with a backup checkpoint on the slower processors.

DUPLEX (Without Backup) on DASD

Define a single checkpoint data set on DASD by specifying the following initialization statement:

```
CKPTDEF CKPT1=(DSN=dsname,VOL=volser,INUSE=YES),
        MODE=DUPLEX,DUPLEX=OFF
```

DUPLEX (Without Backup) on Coupling Facility

Define a single checkpoint data set on the coupling facility by specifying the following initialization statement:

```
CKPTDEF CKPT1=(STRNAME=strname,INUSE=YES),
        MODE=DUPLEX,DUPLEX=OFF
```

Effects of Error Situations When DUPLEX=OFF

The effects of an I/O error to your checkpoint data set can be disastrous:

- If an I/O error occurs and the checkpoint volume becomes unavailable or damaged, you might be able to enter the checkpoint reconfiguration dialog from an active member of your MAS configuration and forward the data set to a new location.
- If your member fails while losing the checkpoint volume and there are no other active members from your MAS configuration, you will lose all checkpointed data.

You can lessen the possibility of causing such a disruption to JES2 processing by defining a DUPLEX checkpoint data set and by adding the CKPT2= and DUPLEX=ON parameter specification to the CKPTDEF initialization statement. For an example of DUPLEX-mode processing with a backup, refer to “DUPLEX-Mode Processing (With Backup)” on page 212.

The complexity of DUAL processing is not required in a single-member environment.

DUAL-Mode Processing

Whereas DUPLEX-mode checkpoint processing uses two checkpoint data sets in a primary-duplex scheme (as described above), DUAL-mode checkpoint processing uses the same two data sets in a “flip-flop” scheme. DUAL mode is recommended if your installation is suffering from degraded system performance due to high checkpoint data set I/O. The use of the change log provides reduced I/O to the checkpoint data set during most, if not all, update accesses by a member of your multi-access spool configuration.

Note that if any checkpoint data set resides on a coupling facility structure, you cannot use DUAL mode.

Example of DUAL Mode in a Two-Member MAS Configuration

Consider the basic example illustrated in Figure 41 on page 218. The definition of this checkpoint configuration example is:

```
CKPTDEF CKPT1=(DSN=dsname,VOL=volser,INUSE=YES),
        CKPT2=(DSN=dsname,VOL=volser,INUSE=YES),
        MODE=DUAL
```

Assume member JESA acquires the checkpoint RESERVE.

- A** It must first read from the most current checkpoint data set to obtain current JES2 queue and system data. For purposes of this discussion, assume CKPT1.
 - B** JESA will then write to the CKPT2 data set (and every tenth write will also be to the CKPT1 data set).
 - C** If JESB now gains control of the checkpoint, it will read from CKPT2 and
 - D** Write to CKPT1 (and every tenth write will also be to the CKPT2 data set).
- Each successive cycle will then continue that alternating (flip-flopping) procedure.




Figure 41. Checkpoint Data Set Processing, DUAL Mode, Two-Member Multi-Access Spool Configuration

Example of DUAL Mode in a Three-Member MAS Configuration

Individual members do not always read and write to the same CKPTn data set. However, the member performing a read always uses the checkpoint data set last updated. The sequence of reads depends upon how many members you have in your MAS configuration and the specifications you have assigned to the queue control parameters (DORMANCY= and HOLD= on the MASDEF initialization statement). To illustrate this condition, a second, more complex example follows; refer to Figure 42 on page 220.

Assume a 3-member multi-access spool configuration; members named JESA, JESB, and JESC and the DUAL checkpoint data sets named CKPT1 and CKPT2. As in the example above, assume JESA obtains checkpoint data set control.

- A** JESA initially reads from CKPT1 and writes to CKPT2.
- B** JESB now gains control, and reads from CKPT2 and writes to CKPT1.

To this point, all I/O is the same as the first example presented in Figure 41 on page 218. For simplicity, let's assume JESC now gains control.

- C** JESC reads from CKPT1 and
- D** Writes to CKPT2.
- E** When JESA again gains control, during its next checkpoint cycle, it reads from CKPT2 and
- F** Writes to CKPT1.

As noted above, this is a simplistic view without regard for your specific queue control parameter specification. The ordering of reads and writes can be rather complicated, because any one member does not always read or write to a particular data set in DUAL mode. For example, should an error occur, you cannot assume that if the error occurred on JESB, CKPT2 is at fault. With this background of processing modes, you will be better able to understand the checkpoint reconfiguration process should you need to recover from an error or decide to alter your checkpoint data set definition.




Figure 42. Checkpoint Data Set Processing -- DUAL Mode -- Three-Member Multi-Access Spool Configuration

Accessing the CKPTn Data Set in a MAS

There are two basic methods of operating a multi-access spool (MAS) configuration to provide individual members access to the checkpoint data set: a controlled environment and a contention-driven environment. This section discusses how you can control your multi-access spool configuration to prevent performance problems caused by the need to access the checkpoint.

Controlled Checkpoint Data Set Access

The recommended method of checkpoint access in a multi-access spool environment is a “controlled” environment where each member is allowed limited and regulated data set access. Use the queue control initialization parameters, `HOLD=` and `DORMANCY=`, on the `MASDEF` initialization statement to control how individual members contend for checkpoint data set control and the length of time each phase takes to complete.

The objective of setting the queue control parameters, `HOLD=` and `DORMANCY=` on the `MASDEF` initialization statement, is to balance access to the checkpoint data set based on the workload of each member in a multi-access spool (MAS) configuration. These parameters allow each member adequate access to the shared job and output queues (that is, the checkpoint data set).

HOLD= Parameter on the MASDEF Statement

The `HOLD=` parameter specifies the minimum time interval that a member will hold the checkpoint data set after acquiring it. If set properly, this parameter can reduce the thrashing back and forth between members that could occur in a contention-driven environment.

The actual time that the checkpoint data set is reserved for a member (and unavailable to others) is the sum of:

1. If the checkpoint data set resides on DASD, the length of time it takes to set the `RESERVE`.
2. Regardless of where the checkpoint data set resides, the length of time it takes to read the `MASTER RECORD`, read the change log (if operating in `DUAL` mode) and changed 4K records.
3. The value specified on `HOLD=`.
4. The length of time it takes to write the changed records to the checkpoint data set.

Setting `HOLD=` too high needlessly locks out other members in the configuration. Setting it too low causes more delays in local JES2 processing and requires more frequent access (and overhead). A good initial value is 50 (0.5 seconds).

This parameter defaults to 99999999 (11+ days), which should be used only in a single-member environment. If you take this default in a multi-access spool configuration consisting of two or more JES2 members, you will effectively prevent other MAS members from accessing the checkpoint.

DORMANCY=(mmmm,nnnn) Parameter on the MASDEF Statement

The `DORMANCY=` parameter specifies both the minimum time interval (mmmm) that a member must wait, after releasing the checkpoint data set, before attempting to regain control of it and the maximum time interval (nnnn) that this member is allowed to wait before attempting to acquire the checkpoint data set. This parameter

and the HOLD= parameter can prevent one member of the configuration from monopolizing the checkpoint data set by acquiring it too frequently.

DORMANCY(mmmm) Specification: Setting (mmmm) too high will increase delays in JES2 processing on this member. Setting it too low will create excessive contention with other members in the configuration.

A good initial value for a particular member is the sum of:

1. All HOLD= values for all other members in the configuration.
2. The length of time it takes to read and write the checkpoint. If the checkpoint data set resides on DASD, a good initial estimate for calculating this length of time on DASD is 15 (that is 0.15 seconds per member to both read and write the checkpoint).

If the checkpoint data set resides on a coupling facility structure, checkpoint I/O is even quicker, because it does not have to set the hardware RESERVE or read the change log.

The default for the DORMANCY(mmmm) specification is 100 (1 second).

DORMANCY(nnnn) Specification: This parameter allows an inactive member to periodically scan the work queues to determine if any work for which it is eligible has entered the member from other members in the configuration.

Setting (nnnn) too high will cause this member to bypass opportunities for JES2 to process work. Setting it too low will create more contention with other members in the configuration.

The default, 500 (5 seconds), is a good initial value for the DORMANCY(nnnn) specification.

Member-Specific Parameter Recommendations

When assigning the queue control parameters (HOLD= and DORMANCY= on the MASDEF statement), be aware of the type and amount of workload on the individual members. For example, a heavy batch, TSO/E, print, or RJE processor workload requires more frequent access to the checkpoint data set than a processor in the configuration devoted mainly to non-TSO online applications.

In configurations that consist of members that are unequal in speed, it might be necessary to set parameters to favor slower members. This will prevent those slower members from becoming locked out from access to the checkpoint data set. Such parameter manipulation is less crucial when the checkpoint data set resides on a coupling facility structure. The coupling facility lock ensures equity by not locking out slower members, so the lower (mmmm) DORMANCY= variable provides little benefit. However, if you set the maximum DORMANCY= variable too high, the coupling facility lock that JES2 uses might not be able to detect the lockout time. The following are recommended queue control parameter settings for specific multi-access spool configurations and processing requirements.

- If running a single-processor, the following parameter specifications might be good initial values because there are no other processors waiting to gain access to the queues.

MASDEF HOLD=99999999,DORMANCY=(10,500)
--

- If running a member under VM, that is sharing queues with production members, the following parameter specifications might be good initial values in order to

minimize the delays due to VM members holding the checkpoint.

```
MASDEF HOLD=0,DORMANCY=(200,1000)
```

- If running a member with heavy-batch, heavy-TSO, or printing (including RJE), the following parameter specifications might be good initial values:

```
MASDEF HOLD=50,DORMANCY=(100,400)
```

- If running a member with an online system that does not need JES2 services very often, the following parameter specifications might be good initial values:

```
MASDEF HOLD=40,DORMANCY=(200,1000)
```

Contention-Driven Checkpoint Data Set Access

The other type of checkpoint data set access is a contention environment, in which the members compete for checkpoint data set control. If DORMANCY=(0,100) is specified, a member attempts to regain access as soon as it needs access (when a processor control element (PCE) requests access).

Some forms of contention-driven access can provide benefits. Setting a low HOLD= value (HOLD=10) and a low minimum dormancy value can benefit a response-oriented configuration where members are of equal size and strength. This type of checkpoint control (or lack of control) has the advantage of ensuring that a member is always requesting the checkpoint. As a result of the low HOLD= value, no member retains the data set for too long.

However, contention-driven access has the disadvantage of causing potential member lockout and severe member degradation in a MAS environment.

Replacement Data Set (NEWCKPTn) Definition

You can specify replacement checkpoint data set definitions to ease recovery from checkpoint I/O errors and the subsequent loss of checkpoint data set access. All 4 checkpoint data sets (NEWCKPTn and CKPTn) must have unique names. For checkpoint data sets residing on DASD, you can have the same DSNAME= value if the VOLser= specification is different. For checkpoint data sets residing on a coupling facility structure, the STRNAME= parameters must be different. Specify replacement checkpoint data sets on either DASD or on coupling facility, regardless of what has been specified on the CKPTn= parameters. Generally, replacement data sets are prefixed with SYSn to provide a complete data set name. For consistency in the following discussion, SYS1.REPLACE1 and SYS1.REPLACE2 are used for the NEWCKPT1= and NEWCKPT2= parameter specifications.

These replacement data set definitions can also be used in non-error situations, such as scheduled hardware maintenance. In both DUPLEX and DUAL mode, NEWCKPT1 provides the replacement definition for CKPT1 and NEWCKPT2 provides the replacement definition for CKPT2.

Space Allocation for NEWCKPTn Data Sets

The space you allocate for the NEWCKPTn data sets (both on DASD and on a coupling facility) should be sufficient to hold all the information in its primary, CKPTn, counterpart. Therefore, allocate this space as at least equal to that

allocated for the CKPTn data sets. (For further information, refer to the “Syntax for Checkpoint Space Allocation on DASD” on page 205.)

If these data sets are not defined in your initialization data, JES2 will not provide default data sets, but you can define these data sets during a checkpoint reconfiguration dialog. If defined at initialization, these data sets are **only defined** and **not allocated**.

To respecify the CKPTn data set, you must define the respective NEWCKPTn data set information using one of four methods. These methods are presented in order of recommendation.

Specify the NEWCKPTn Data Set during Initialization

Define the replacement checkpoint data sets by adding the NEWCKPT1= and NEWCKPT2= parameters to the same CKPTDEF initialization statement that you use to define your primary (CKPT1 and CKPT2) data sets. These data set are only defined to JES2; they are not allocated until they are put into use during the checkpoint reconfiguration dialog.

For checkpoints on DASD:

```
CKPTDEF NEWCKPT1=(DSNAME=dsname,VOLSER=volser),
        NEWCKPT2=(DSNAME=dsname,VOLSER=volser),
```

For checkpoints on coupling facility:

```
CKPTDEF NEWCKPT1=(STRNAME=strname),
        NEWCKPT2=(STRNAME=strname),
```

Specify the NEWCKPTn Data Set through the \$T CKPTDEF Command

These data sets are only defined to JES2 at some time after initialization; they are not allocated until they are put into use during the checkpoint reconfiguration dialog.

If you have not specified a value for a NEWCKPTn parameter in the initialization data set, a \$D CKPTDEF,NEWCKPT1 operator command displays the following:

```
$HASP829 CKPTDEF NEWCKPT1=(DSNAME=,VOLSER=)
```

To remove a NEWCKPTn value without specifying an alternative value, specify:

```
$T CKPTDEF,NEWCKPT1=(DSNAME=,VOLSER=) | (STRNAME=)
```

To specify DASD values for NEWCKPTn:

```
$T CKPTDEF,NEWCKPT1=(DSN=dsname,VOL=volser),
        NEWCKPT2=(DSN=dsname,VOL=volser)
```

To specify coupling facility values for NEWCKPTn:

```
$T CKPTDEF,NEWCKPT1=(STRNAME=strname),
        NEWCKPT2=(STRNAME=strname)
```

Specify the NEWCKPTn Data Set during Reconfiguration (\$HASP271)

If these data sets have not been pre-defined (by initialization statement or by operator command), and you want to define the NEWCKPTn specifications during the dialog, the operator can specify the DSName and VOLser or the STRname= attributes by responding:

```
CKPTDEF NEWCKPTn={ (DSName=,VOLser=) | (STRNAME=) }
```

in response to the

```
$HASP271 CHECKPOINT RECONFIGURATION OPTIONS  
$HASP272 ENTER RESPONSE (ISSUE D R,MSG=$HASP271 FOR RELATED MSG)
```

and message pair. (The reconfiguration dialog is more fully discussed in “Checkpoint Reconfiguration, An Overview” on page 228.)

JES2 will dynamically allocate these data sets at this time.

Specify the NEWCKPTn Data Set during Reconfiguration (\$HASP282)

If you attempt to replace the NEWCKPTn specifications with those of the NEWCKPTn data set, and it has not been previously defined or it has become unavailable due to an I/O error, JES2 will issue \$HASP282 NEWCKPTn DSN NULL and \$HASP272 ENTER RESPONSE or the \$HASP282 NEWCKPTn DSNAME, VOLUME, AND STRNAME ARE NULL and \$HASP272 ENTER RESPONSE message pair.

If you want to define the NEWCKPTn data set at this time, you must respond:

```
CKPTDEF NEWCKPTn={ (DSName=,VOLser=) | (STRNAME=) }
```

See *z/OS JES2 Messages* for a complete description of all the valid responses to the \$HASP282 message.

Placement of the NEWCKPTn Data Sets

The volumes you assign to the two replacement NEWCKPTn data sets need not be unique, although IBM recommends that these two data sets reside on a separate volume from their primary data set counterparts. Both backup data sets can be specified on a single volume. This will generally provide sufficient protection from checkpoint data set loss; however, this configuration can cause some degree of performance degradation until the unavailable data set or volume is again available.

If the checkpoint data set resides on a coupling facility structure, you can exercise some control over its placement through the use of preference and exclusion lists. For more information about how to specify these lists in your coupling facility resource management (CFRM) policy, see *z/OS MVS Setting Up a Sysplex* and *z/OS Communications Server: IP Migration*.

Using the NEWCKPTn Data Sets

In both error and non-error situations, the NEWCKPTn data set specifications can be used during the checkpoint reconfiguration dialog to replace the CKPTn specifications. For example, if an error occurs on CKPT1, JES2 **forwards** the CKPT1 specification to the NEWCKPT1 specification to replace the unavailable CKPT1 data set. (If the NEWCKPT1 data set has not been pre-defined, or has already been used, the operator can dynamically define it during the dialog. See “Replacement Data Set (NEWCKPTn) Definition” on page 223 for further information.)

Forwarding is the process of replacing the CKPTn data set name and volume serial or structure name (if defined on a coupling facility) with the specifications of its NEWCKPTn counterpart (NEWCKPT1 for CKPT1 and NEWCKPT2 for CKPT2), and the copying of the in-storage version of the checkpoint data to this newly defined CKPTn data set. The NEWCKPTn data set specification then becomes null.

The operator forwards the CKPTn specifications by selecting the appropriate option to the \$HASP271 CHECKPOINT RECONFIGURATION OPTIONS and \$HASP272 ENTER RESPONSE message pair. (Refer to \$HASP271 in *z/OS JES2 Messages* for these options and an explanation of each.) When the forwarding process is complete, the other members will automatically begin using this newly defined CKPTn data set.

For an example of the forwarding process, refer to Figure 43 on page 227 which uses the following checkpoint data set definition:

Note that this example applies equally to checkpoints residing on a coupling facility structure, except that the STRname= subparameter replaces the DSN= and the VOL= specifications in the following examples.

A Your configuration is running in DUAL mode (that is MODE=DUAL) and your initialization data set has defined a backup data set for both primary data sets. These are specified as SYS1.REPLACE1 and SYS1.REPLACE2 both on volume CHECK3.

```
CKPTDEF      CKPT1=(DSN=SYS1.JESCKPT1,VOL=CHECK1),
              CKPT2=(DSN=SYS1.JESCKPT2,VOL=CHECK2),
              NEWCKPT1=(DSN=SYS1.REPLACE1,VOL=CHECK3),
              NEWCKPT2=(DSN=SYS1.REPLACE2,VOL=CHECK3)
```

B Assume an I/O error occurs to the CHECK2 volume while reading the CKPT2 data set. Data set SYS1.JESCKPT2 on volume CHECK2 becomes unavailable. Effectively, it no longer exists.

C You can **forward** CKPT2 from the unavailable data set whose name is SYS1.JESCKPT2 on volume CHECK2 to SYS1.REPLACE2 on volume CHECK3 because you have previously defined NEWCKPT2 in your initialization data set. Remember, although you have not altered your initialization data set (it remains as shown in the example) you have altered the data set specifications to the following:

```
CKPT1=      (DSN=SYS1.JESCKPT1,VOL=CHECK1)
CKPT2=      (DSN=SYS1.REPLACE2,VOL=CHECK3)
NEWCKPT1=(DSN=SYS1.REPLACE1,VOL=CHECK3)
NEWCKPT2=(DSN=,VOL=)
```

Note: Following a JES2 restart, the checkpoint data set definitions, as defined in your initialization data set, are read. If the checkpoint data sets have been forwarded, and you have not updated your initialization data set to reflect the new data set definitions, JES2 will use the definitions to provide a pointer to the new data set definitions. However, If you have updated your initialization data set to reflect the new data set definitions, JES2 will use these definitions without doing any forwarding.




Figure 43. Example of Checkpoint Data Set Forwarding

Note that CKPT2 is now provided with a new data set name and volume specification (the specification provided by forwarding it to the NEWCKPT2 specification). The NEWCKPT2 specification is now null.

Checkpoint Reconfiguration, An Overview

The checkpoint reconfiguration facility allows you to dynamically redefine the checkpoint data set definitions for your JES2 multi-access spool (MAS) configuration. Whether the data sets reside on a DASD volume or on a coupling facility structure, the reconfiguration, through its operator dialog allows you to:

- Replace a checkpoint data set.
- Discontinue the use of a checkpoint data set.
- Resume using a previously suspended checkpoint data set.
- Terminate JES2 during the dialog.
- Start using a new checkpoint data set.

CAUTION:

JES2 does not support moving the checkpoint data set from one volume serial to another unless the checkpoint dialog is used.

Additionally, you can either enter a checkpoint reconfiguration dialog to change the DASD to any supported type or model or change the DASD while involved in a dialog initiated for other reasons. Device types used to hold the checkpoint data set can be a mix of any JES2-supported DASD (refer to “Appendix A. IBM Devices Supported by JES2 and How to Use Them” on page 379 for a list of these devices) and/or coupling facility structure(s).

If your checkpoint is on a coupling facility and all you want to do is move it to a different coupling facility, then you can use the SETXCF command to start a rebuild instead of using checkpoint reconfiguration. However, only checkpoint reconfiguration can move the checkpoint from a coupling facility to DASD. See “Moving a JES2 Checkpoint to a Coupling Facility Using System Managed Rebuild” on page 244 for more information.

Depending on the situation, either JES2 or the operator can initiate the checkpoint reconfiguration process. The following situations initiate a checkpoint reconfiguration dialog:

- JES2-initiated:
 - During initialization processing:
 - Either JES2 could not determine the checkpoint data set specifications, or JES2 requires operator verification of the data set specifications.
 - You specified PARM=RECONFIG as a JES2 start option.
 - You specified RECONFIG=YES on the CKPTDEF initialization statement.
For a discussion of the JES2-initiated checkpoint reconfiguration at initialization, see “Initialization” on page 233.
 - Due to I/O error:
JES2 automatically initiates a reconfiguration when an I/O error occurs during a read or write of the checkpoint data set. For a discussion of the JES2-initiated checkpoint reconfiguration see “I/O Error” on page 234.
 - Due to coupling facility structure becomes volatile:
As result of processing based on your CKPTDEF VOLATILE= specification when a coupling facility on which a checkpoint resides becomes volatile. A coupling facility structure is considered volatile if when power to the coupling facility is lost, all data on the facility is lost. A volatile structure might not be an immediate problem, but is serious enough that JES2 prompts you to take precautions to prevent potential data loss.

Note that a coupling facility is always considered volatile unless you have taken measures to protect against the loss of power to that coupling facility. Refer to *ES/9000 and ES/3090 PR/SM Planning Guide* for a description of how to monitor the volatility of coupling facilities.

For a discussion of the JES2-initiated checkpoint reconfiguration due to the coupling facility structure becoming volatile, see “Volatile Coupling Facility” on page 237.

- Operator-initiated:

Depending on your installation’s use of DASD or coupling facility structures or both to maintain your checkpoint data, you might need to occasionally change your checkpoint definitions. For example, you might choose to initiate a checkpoint reconfiguration because the device on which the checkpoint data set(s) resides is scheduled for service. However if your checkpoint is on a coupling facility, it may be simpler to use system managed rebuild to move your checkpoint to another coupling facility. See “Moving a JES2 Checkpoint to a Coupling Facility Using System Managed Rebuild” on page 244 for more information

For a discussion of the operator-initiated checkpoint reconfiguration see “Operator-initiated Entrance into a Checkpoint Reconfiguration Dialog” on page 238.

The reconfiguration allows minimal disruption across all checkpoint data set failures, thus preventing the need for a JES2 restart.

Checkpoint Reconfiguration Concepts

Whenever JES2 detects a situation that requires that it initiate a checkpoint reconfiguration, JES XCF, the JES common coupling services, provide the communication mechanism between the MAS members. By default, JES2 MAS members join a JES XCF group and are mapped in a one-to-one relationship with the JES XCF group members. As such, all members are linked through the JES XCF interface and JES2 is able to determine which MAS member will be considered the **driving member** for the reconfiguration. The driving member is the member that 1) has the most up-to-date version of the checkpoint data in-storage and 2) will be the member that directs (or drives) the other members through the reconfiguration process. All other members are referred to as **non-driving members**. Once the reconfiguration process begins, if the driving member subsequently fails, JES2 selects the next best candidate to replace it as the new driving member. (If you require further background information on the JES common coupling services, refer to *z/OS MVS Programming: JES Common Coupling Services* or for recommendations on configuring your MAS in a sysplex environment refer to *z/OS MVS Setting Up a Sysplex*.)

Preparing for Checkpoint Reconfiguration

Depending on whether you maintain your checkpoint on a coupling facility structure or DASD, there are a few steps you should take to ease an unplanned checkpoint reconfiguration.

Becoming involved in a checkpoint reconfiguration can have serious consequences if you do not understand the implications of the choices JES2 presents through the dialog messages. Be certain you and your staff understand the definitions as well as the concepts explained in this section. (The checkpoint dialog messages and the options they present are fully explained in *z/OS JES2 Messages* as well.)

IBM highly recommends that you use a non-production, test JES2 MAS to 'practice' using the reconfiguration dialog in order to establish your recovery procedures. Remember, JES2 will automatically enter a checkpoint reconfiguration if a checkpoint I/O error occurs.

JES2-initiated Due to I/O Error

You can minimize or eliminate operator involvement during the checkpoint reconfiguration process prompted by JES2 due to an I/O error by defining replacement checkpoint data set(s) in advance. Further, specify OPVERIFY=NO on the CKPTDEF initialization statement or use the \$T CKPTDEF OPVERIFY=NO command to eliminate operator involvement.

During a checkpoint reconfiguration due to an I/O error, JES2 attempts to allocate and use a replacement checkpoint data set. If you do not predefine a replacement checkpoint data set, JES2 prompts the operator for the DASD definition (name and volume serial number) or coupling facility structure name of a suitable replacement. Several prompt messages (for example, \$HASP273 and \$HASP282) allow you to tell JES2 to suspend using a particular data set, modify CKPTDEF initialization statement options, cancel the reconfiguration, or terminate JES2. Use the NEWCKPT1= and NEWCKPT2= options on the \$T CKPTDEF command (outside a checkpoint reconfiguration) to predefine replacement checkpoint data sets.

Predefining Replacement Checkpoint Data Sets

You can minimize the chance of errors and operator involvement during a checkpoint reconfiguration by defining and allocating replacement checkpoint data sets or structure definitions. Predefining replacement checkpoint data sets, however, does not guarantee that JES2 will be able to successfully allocate them during the checkpoint reconfiguration process.

JES2 can specify a replacement checkpoint data set on DASD. This procedure requires that you minimally perform step 1; step 2 is optional.

1. You can specify your backup checkpoint data set (NEWCKPTn) either on the CKPTDEF initialization statement or by operator command(\$T CKPTDEF,NEWCKPTn=(DSN=...,VOL=...)) .
Using this definition, JES2 can dynamically allocate the space for this data set if this data set did not previously exist on the volume.
2. To ensure that the space for the data set is available if needed, pre-allocate the space on the volumes for your replacement checkpoint data sets. See "Replacement Data Set (NEWCKPTn) Definition" on page 223 for information about defining replacement checkpoint data sets. See "Syntax for Checkpoint Space Allocation on DASD" on page 205 for information about how to determine the space requirements for checkpoint data sets.

If you maintain your checkpoint on a coupling facility structure, be certain to have previously defined the structure for NEWCKPTn=(STRNAME=) in a coupling facility resource management (CFRM) policy. JES2 cannot dynamically add this name to the CFRM policy. Therefore, if you expect JES2 to forward a checkpoint to a new structure, and you have failed to define the structure in the CFRM policy, JES2 will prompt the operator for a valid checkpoint specification. Refer to *z/OS MVS Setting Up a Sysplex* for information on defining coupling facility structure and a CFRM policy.

Using the Checkpoint Reconfiguration Dialog

As stated earlier, either JES2 or the operator can initiate the reconfiguration process. This section provides some important concepts you should understand

before entering a checkpoint reconfiguration dialog. It presents some considerations for checkpoint message routing, how you can determine why JES2 entered a particular type checkpoint reconfiguration, and some very important differences for the dialog responses of *CANCEL* and *TERM*.

Message Routing During a Checkpoint Reconfiguration

The reason JES2 entered a checkpoint reconfiguration, the message route code, and your installation's specification of the MVS parameter MSCOPE= on the MVS CONSOLxx member of SYS1.PARMLIB all determine how the checkpoint reconfiguration messages are routed.

Based on reconfiguration entrance type, messages are directed as follows:

- Operator initiated - the messages are directed to the console that requested the dialog

Therefore, if the MVS system to which this console is attached subsequently fails, the checkpoint reconfiguration messages might not be displayed on any console. To prevent this situation, when planning your sysplex console configuration consider the systems to which your consoles are attached. Refer to *z/OS MVS Initialization and Tuning Reference* for a description of the GROUP and NAMES parameters on CNGRPxx and the ALTGRP, MSCOPE, and UD parameters on CONSOLxx. Also refer to *z/OS MVS Planning: Operations* for recommendations on how to define your consoles to be certain messages are routed as expected in a sysplex environment.

- JES2 initiated - the messages are directed to consoles based on their route code(s)

The console on which reconfiguration messages appear is influenced by which member drives the checkpoint reconfiguration and your MSCOPE= specification on the CONSOLxx parmlib member. Also, if during a checkpoint reconfiguration, the driving member fails, the messages issued by the new driving member might appear on a different set of consoles based on MSCOPE= specifications.

Depending on your MSCOPE= specifications for your consoles, exception messages issued by non-driving members, such as \$HASP424, might not appear on the same console on which \$HASP235 and \$HASP272 messages are displayed.

Messages are directed to console by route code or console ID. Additionally, some messages are also issued only to the HDRCPY log. Those issued to the HDRCPY log are useful for diagnostic purposes and allow you to follow the progress of the reconfiguration on each member during a checkpoint reconfiguration. For example, all JES2 members within the MAS issue \$HASP285, \$HASP233, and \$HASP255 to HDRCPY.

Determining the Reason for a Checkpoint Reconfiguration

Multiple members can enter a checkpoint reconfiguration concurrently for any number of reasons. For example, you might request an operator-initiated reconfiguration at the same time an I/O occurs. If so, JES2 determines which reason takes precedence in the following order:

1. I/O error on CKPT1
2. I/O error on CKPT2
3. Coupling facility on which the checkpoint resides becomes volatile
4. Operator request.

Message \$HASP233 REASON FOR JES2 CHECKPOINT RECONFIGURATION IS *reconfiguration-reason* informs you for which problem JES2 entered the reconfiguration.

If an I/O occurs on CKPT1 and CKPT2 on separate members at the same time, JES2 enters the reconfiguration for the I/O error on CKPT1. Once that reconfiguration is complete, JES2 then enters a subsequent reconfiguration if the problem with CKPT2 still exists. JES2, however, does not enter subsequent reconfigurations if a concurrent coupling facility became volatile or an operator requested a dialog.

Dialog Options: CANCEL and TERM

Several WTOR messages throughout the dialog give an option of 'CANCEL' or 'TERM'. The two options, CANCEL and TERM are quite different in their meaning, and the two are never presented as options at the same time.

- TERM, an option within I/O error checkpoint dialogs

If selected, TERM indicates to JES2 to terminate (that is, force abnormal termination) of **all** members that experienced an I/O error on the CKPTn being processed by this checkpoint reconfiguration as indicated by \$HASP233. The remaining members continue processing, but terminated members require a restart.

\$HASP233 provides which checkpoint (CKPT1 or CKPT2) experienced the I/O error; it also provides the number of members affected. Refer to "Determining the Reason for a Checkpoint Reconfiguration" on page 231 for a discussion of the precedence of reconfiguration types if multiple checkpoint problems occur.

\$HASP275 provides an individual message for each affected member; it also provides a \$Knn reason code specific to the member that issued the message. If you reply TERM in response to \$HASP272, this reason code becomes the \$Knn error code reflected in the \$HASP095 message when the member abnormally terminates. To verify which members received the \$HASP275 message and determine the members that will be affected (terminated) by a reply of TERM, issue `D R,L,CN=(ALL),MSG=$HASP275` (This MVS command assumes that `CONDEF CONCHAR=$` on all MAS members.).

If you need to terminate a single JES2 member while within a reconfiguration, you need to complete the following 2-step process:

1. Enter the `$P JES2,ABEND` command

JES2 responds with:

```
$HASP697 COMMAND PURGED--RECONFIGURATION DIALOG IN PROGRESS
```

2. Enter the `$P JES2,ABEND,FORCE` command.

TERM is more serious and always causes all member(s) experiencing the I/O on CKPTn to abend. IBM does not recommend its use because the remaining member(s) might subsequently reenter a checkpoint reconfiguration due to the same error situation. If the error situation is temporary, you should forward the checkpoint (options '1' or '2') or suspend using the checkpoint (options '5' or '6') and immediately reenter a new reconfiguration dialog to resume (options '7' or '8') using the suspended checkpoint.

- TERM, an option within JES2-initiated dialogs for initialization

A response of TERM to the \$HASP289 and \$HASP272 message pair while within a JES-initiated dialog for initialization affects (terminates) the initializing member only. (A JES2-initiated initialization dialog has a scope of the single member, it never affects other MAS members.)

- CANCEL, an option for other reconfiguration dialog types.

CANCEL provides the operator a means to simply end the dialog and allow processing to continue as before. If you replied CKPTDEF to change CKPTn or NEWCKPTn and then CANCEL a reconfiguration, those changes are lost.

Attention: Although TERM and CANCEL are never presented simultaneously as options on the same message, if you inadvertently specify either TERM or CANCEL when that option is **not** presented, JES2 will treat that response as a synonym for the presented option. For example, if \$HASP273 offers an option of TERM and you reply CANCEL in response to \$HASP272, JES2 **terminates** all JES2 members that experienced an I/O error; JES2 does not simply end the dialog.

JES2-initiated Entrance into the Dialog

JES2 will enter a checkpoint reconfiguration for any of these reasons:

- To complete initialization processing
- To correct an I/O error to the checkpoint data set
- To move the checkpoint off a volatile coupling facility structure.

Initialization

JES2 can enter the checkpoint reconfiguration dialog during initialization processing for the following reasons:

- JES2 could not determine, or required verification of, the checkpoint data set specifications
- You specified PARM=RECONFIG as a JES2 start option
- You specified RECONFIG=YES on the CKPTDEF initialization statement.

JES2 automatically enters a dialog either because of an error condition (as noted in the first instance above) or because you have requested it to do so (as noted in the second and third instances).

A checkpoint reconfiguration entered at initialization is limited to the initializing member only; it is not a multi-system reconfiguration as are all other reconfiguration types. As such, the reasons for entrance can be unique. For example, consider the following scenario:

1. An I/O error occurred and CKPTn was forwarded at that time
2. The I/O error prevented JES2 from writing the forwarding information into the data set in error or possibly from reading it during this JES2 initialization. Refer to “Using the NEWCKPTn Data Sets” on page 225 for a discussion of JES2 checkpoint data set forwarding.
3. You did not update the initialization data set to reflect the new checkpoint data set definition(s)
4. When initializing, JES2 will prompt the operator for the CKPTn definition(s) currently being used by the other MAS members.

Note: After completing all interactions with the operator, JES2 will verify the last written time stamp of the data set it will read the checkpoint from. The checkpoint is read from either the CKPTn specified on the PARM= on JES2 start or as determined by JES2 processing. This verification is an attempt to verify that JES2 is reading from the correct checkpoint data set. Ultimately it is the installations' responsibility to ensure that the correct data sets are used to start JES2. However, some common problems are detected by JES2. Normally, the \$HASP478 message is not highlighted and is issued for informational purposes only. However, if JES2 detects a potential problem with the last written times of the checkpoint data set(s), then the message is highlighted and followed by the \$HASP441 WTOR. When this happens, the installation should verify that the time stamps associated with the data set being matched with the time the MAS was last active and would have last written the checkpoint. If not, then reply 'N' to the \$HASP441 message to terminate in response to \$HASP478.

Example Reconfiguration Dialog at Initialization: The following example illustrates a typical console sequence when the operator initiates a checkpoint reconfiguration dialog by specifying RECONFIG on the start JES2 command. The system configuration is based on the following checkpoint definition.

```
CKPTDEF CKPT1=(DSN=SYS1.JES2CKPT1,VOL=CHECK1,INUSE=YES),
         CKPT2=(DSN=SYS1.JES2CKPT2,VOL=CHECK2,INUSE=YES),
         NEWCKPT1=(DSN=SYS1.JES2REP1,VOL=CHECK3),
         NEWCKPT2=(DSN=SYS1.JES2REP2,VOL=CHECK4),
         MODE=DUAL,OPVERIFY=YES
```

Assume you need to restart JES2 to change the MODE= specification from DUAL to DUPLEX. This change requires an all-member warm start. Restart JES2 by entering: *S JES2,PARM='WARM,RECONFIG'*... in order that JES2 will enter a reconfiguration dialog to allow you to make the change. You then receive the following series of messages:

1. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTED - JES2 INITIALIZATION
2. \$HASP289 CKPT1 AND/OR CKPT2 SPECIFICATIONS ARE REQUIRED... VALID RESPONSES ARE...
3. \$HASP272 ENTER RESPONSE
4. Operator response: R nn,CKPTDEF MODE=DUPLEX
5. \$HASP829 CKPTDEF ...,MODE=DUPLEX,...
6. \$HASP289 CKPT1 AND/OR CKPT2 SPECIFICATIONS ARE REQUIRED... VALID RESPONSES ARE...
7. \$HASP272 ENTER RESPONSE
8. Operator response: R nn,END

Attention: If, on a JES2 restart, you specify RECONFIG as an option in response to the \$HASP426 SPECIFY OPTIONS message or you have previously added RECONFIG to the EXEC statement of the JES2 PROC, JES2 will ignore all prior checkpoint data set forwarding performed by previous checkpoint reconfigurations. JES2 will override all forwarding and use the checkpoint data set definitions as defined in your initialization data set. (Refer to “Using the NEWCKPTn Data Sets” on page 225 for a discussion of JES2 checkpoint data set forwarding.) If this is inappropriate to your restart situation, be certain to have either redefined your checkpoint data sets in your initialization data set or **do not** use the RECONFIG option. Refer to “Specifying the Start Options” on page 27 for information on specifying JES2 start options and *z/OS MVS JCL Reference* for specifying the JES2 PROC statement.

I/O Error

If an I/O error on a checkpoint data set occurs, JES2 enters checkpoint reconfiguration processing automatically. An I/O error can occur during either a read or write of the checkpoint data set on any member. Unless a concurrent member failure occurs, JES2 automatically initiates the checkpoint reconfiguration dialog on all members in your MAS.

When JES2 initiates a checkpoint reconfiguration, the degree of operator involvement depends on whether:

- Operator verification is not desired (OPVERIFY=NO on CKPTDEF)
- You have predefined a replacement checkpoint data set (NEWCKPTn= on CKPTDEF)
- An error occurs during the reconfiguration. (JES2 normally performs reconfiguration processing without operator involvement if the preceding two

conditions are met. However, if JES2 encounters an error when attempting to complete an automatic reconfiguration, JES2 initiates an operator dialog to complete reconfiguration processing. Therefore, be certain to have a knowledge of the dialog procedure and have a data center procedure in place to handle such possibilities.)

Minimizing Operator Involvement: If you suppress operator verification **and** you have predefined a replacement checkpoint data set, JES2 automatically forwards the checkpoint data set that experienced the I/O error. To suppress operator verification, specify OPVERIFY=NO on the CKPTDEF initialization statement or on a \$T CKPTDEF command. Automatic forwarding allows you to minimize disruption to your production systems. JES2 follows your predefined instructions and forwards the checkpoint data set as specified on the CKPTDEF statement. You are not prompted to change those instructions at reconfiguration time, thereby reducing the time required to complete checkpoint reconfiguration.

If you suppress operator verification (that is, if you specify OPVERIFY=NO) and NEWCKPTn= has been specified, JES2 takes the following default reconfiguration actions:

- Rather than issuing \$HASP273, JES2 replaces the checkpoint data set with its replacement data set defined on the NEWCKPTn parameter of the CKPTDEF statement.
- Rather than issuing message \$HASP278 (with the CREATE option), when JES2 cannot locate the specified replacement checkpoint data set, JES2 automatically creates one on the previously specified DASD volume, or JES2 can connect to a new coupling facility structure, but **only** if your coupling facility resource management (CFRM) policy has defined the structure.

Note: If however, OPVERIFY=YES and a CFRM policy does exist, you will be prompted to define a replacement checkpoint at this time.

Requesting Operator Involvement: You can request that JES2 prompt the operator during the checkpoint reconfiguration process by specifying OPVERIFY=YES on the CKPTDEF initialization statement or on a \$T CKPTDEF command. With operator verification enabled, the operator can:

- Accept the new checkpoint configuration. - Reply CONT
- Terminate all JES2 members that encountered I/O errors on the CKPTn being processed. Refer to “Dialog Options: CANCEL and TERM” on page 232 for a description of this procedure. - reply TERM
- Discontinue using the specified data set. - Reply DELETE
This option (DELETE) is only available if the reconfiguration is due to an I/O error and both CKPT1 and CKPT2 are being used.
- Specify a different replacement checkpoint data set. - Reply CKPTDEF (with operands)

If you enable operator verification, JES2 prompts the operator during the checkpoint reconfiguration dialog with several messages, the most likely message pairs to be issued and requiring a response are:


```

$HASP273 JES2 CKPTn DATA SET WILL BE ASSIGNED TO NEWCKPTn
        STRNAME strname | dsname ON VOLUME volser
        VALID RESPONSES ARE:
:
$HASP272 ENTER RESPONSE

```

-or-

```

$HASP278 UNABLE TO LOCATE OR UNABLE TO USE CKPTn|NEWCKPTn
        STRNAME strname | dsname ON VOLUME volser
        DOES NOT EXIST OR IS NOT USABLE - REFER TO PREVIOUS MESSAGE(S)
        VALID RESPONSES ARE:
:
$HASP272 ENTER RESPONSE

```

Message \$HASP273 is used to request operator validation of the reconfiguration action JES2 is about to take. It is only issued if OPVERIFY=YES or JES2 requires operator involvement due to an unexpected processing condition. Message \$HASP278 indicates that you have not preallocated a backup checkpoint data set or, if allocated, it was specified in error. Message \$HASP273 can be eliminated by being certain you have specified valid NEWCKPTn data set(s) or structures.

Example Reconfiguration Dialog for I/O Error: The following example illustrates a typical console sequence when JES2 initiates a checkpoint reconfiguration dialog with operator verification enabled. The system configuration is based on the following checkpoint definition:

```

CKPTDEF CKPT1=(DSN=SYS1.JES2CKPT1,VOL=CHECK1,INUSE=YES),
        CKPT2=(DSN=SYS1.JES2CKPT2,VOL=CHECK2,INUSE=YES),
        NEWCKPT1=(DSN=SYS1.REPLACE1,VOL=CHECK3),
        NEWCKPT2=(DSN=SYS1.REPLACE2,VOL=CHECK3),
        MODE=DUPLEX,OPVERIFY=YES

```

Assume an I/O error occurs on CKPT2 on member SY1

1. \$HASP275 CKPT2 I/O ERROR - Knn
2. \$HASP233 REASON FOR JES2 CHECKPOINT RECONFIGURATION IS CKPT2 I/O ERROR(S) ON 1 MEMBER(S)
3. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTED - DRIVEN BY MEMBER SY1
4. \$HASP273 JES2 CKPT2 DATA SET WILL BE ASSIGNED TO ...
5. \$HASP272 ENTER RESPONSE
6. Operator response: R nn,CONT
7. \$HASP280 JES2 CKPTn DATA SET...
8. \$HASP255 JES2 CHECKPOINT RECONFIGURATION COMPLETE
9. \$HASP256 FUTURE AUTOMATIC FORWARDING OF CKPT2 IS SUSPENDED UNTIL NEWCKPT2 IS RESPECIFIED. ISSUE \$T CKPTDEF,NEWCKPT2=(...) TO RESPECIFY

In this example, \$HASP256 is a highlighted message and remains on the screen until you issue \$T CKPTDEF,NEWCKPT2=(...).

If you alternatively specified OPVERIFY=NO on the CKPTDEF statement above, message pair \$HASP273 and \$HASP272 is not presented to the operator. All messages issued in a JES2-initiated automated checkpoint reconfiguration are informational and none require response.

If an automatic checkpoint reconfiguration takes place while the operator is away from the console, on return, the only message displayed will be \$HASP256.

Therefore, you can automate a reconfiguration by automating the response to this message only. To do so, establish a pool of replacement checkpoint data sets from which an automated \$T CKPTDEF,NEWCKPTn=(...) reply in response to \$HASP256 can choose a replacement.

Operator Intervention When Errors Occur During a Reconfiguration: JES2 requires operator intervention during a JES2-initiated dialog, if any of the following conditions are true:

- You have not predefined a replacement checkpoint data set (NEWCKPTn=)
 - or -- You have not predefined a replacement structure name defined to a CFRM policy and specified a structure name on NEWCKPTn.
- JES2 cannot allocate the specified replacement checkpoint data set.
- The operator mistakenly specifies an unusable replacement dataset.

Volatile Coupling Facility

JES2 enters a checkpoint reconfiguration if the coupling facility structure on which the checkpoint data set resides becomes volatile and subsequent CKPTDEF VOLATILE= processing determines a checkpoint reconfiguration is required. Note that a coupling facility is always considered volatile unless you have taken measures to protect against the loss of power to that coupling facility. Refer to *ES/9000 and ES/3090 PR/SM Planning Guide* for a description of how to monitor the volatility of coupling facilities.

When forwarding a checkpoint data set to move it from a volatile coupling facility, you could inadvertently forward it to another volatile coupling facility. JES2 issues \$HASP237 to inform you this is the case, and you are prompted to CONT (continue), CANCEL, or define an alternate checkpoint (structure or DASD data set). If you decide to forward your checkpoint to a volatile coupling facility (that is, you respond CONT to message pair \$HASP237 / \$HASP272), JES2 accepts that response and does not provide any further CKPTDEF VOLATILE= processing for this structure while the structure remains volatile.

Example Reconfiguration Dialog for Volatile Coupling Facility: The following example illustrates a typical console sequence when JES2 initiates the checkpoint reconfiguration dialog because the coupling facility on which the checkpoint resides has become volatile. The system configuration is based on the following checkpoint definition:

```
CKPTDEF CKPT1=(STRNAME=SYS1_CKPT1,INUSE=YES),
        CKPT2=(STRNAME=SYS1_CKPT2,INUSE=YES),
        NEWCKPT1=(STRNAME=SYS1_NEWCKPT1),
        NEWCKPT2=(STRNAME=SYS1_NEWCKPT2),
        MODE=DUPLEX,
        DUPLEX=YES,
        OPVERIFY=NO,
        VOLATILE=(ALLCKPT=DIALOG,ONECKPT=DIALOG)
```

Assume the coupling facility on which the structure SYS1_CKPT1 resides becomes volatile. Messages are directed by route code. Refer to “Message Routing During a Checkpoint Reconfiguration” on page 231 for a more complete discussion.

1. \$HASP233 REASON FOR JES2 RECONFIGURATION CHECKPOINT IS
COUPLING FACILITY HAS BECOME VOLATILE
2. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTED - DRIVEN
BY MEMBER SY8
3. \$HASP271 CHECKPOINT RECONFIGURATIONS OPTIONS...VALID
RESPONSES ARE...

4. \$HASP272 ENTER RESPONSE
If the operator did not notice the message that indicated which checkpoint(s) is volatile, the \$D CKPTDEF command is useful to display that information. (A reply of CKPTDEF provides a display of modifiable parameters only and therefore cannot provide this information.)
5. Operator response: R nn,2
6. \$HASP273 JES2 CKPT2 DATA SET WILL BE ASSIGNED TO NEWCKPT2...VALID RESPONSES ARE ...
7. \$HASP272 ENTER RESPONSE
8. Operator response: R nn,CONT
9. \$HASP256 FUTURE AUTOMATIC FORWARDING OF CKPT2 IS SUSPENDED UNTIL NEWCKPT2 IS RESPECIFIED. ISSUE \$T CKPTDEF,NEWCKPT2=(...) TO RESPECIFY
In this example, \$HASP256 is a highlighted message and remains on the screen until you issue \$T CKPTDEF,NEWCKPT2=(...) in step 11
10. \$HASP255 JES2 CHECKPOINT RECONFIGURATION COMPLETE
11. enter: \$T CKPTDEF,NEWCKPT2=(...)

Operator-initiated Entrance into a Checkpoint Reconfiguration Dialog

The operator can initiate a checkpoint reconfiguration dialog; this is generally done to:

- Replace a checkpoint data set
- Update and start (resume) using a checkpoint data set
- Discontinue using a checkpoint data set.

You can enter a reconfiguration dialog at any point in JES2 processing by entering:

\$T CKPTDEF,RECONFIG=YES

Note: Several messages throughout the dialog give the option of 'CANCEL'. If the operator decides to end the reconfiguration process on a member, a response of 'CANCEL' will cause JES2 to exit from the dialog. If you replied CKPTDEF to change CKPTn or NEWCKPTn during the reconfiguration, those changes are lost.

Initiating a reconfiguration dialog on any member causes JES2 to automatically initiate the reconfiguration process on all other active members of the MAS configuration. JES2-operator interaction for the entire dialog, however, is controlled from the console on which the operator initiates the dialog.

Replacing a Checkpoint Data Set

Replacing a checkpoint data set is a relatively simple procedure. Whether or not you have previously defined the corresponding replacement data set will determine how this can be done during the reconfiguration dialog.

If you have previously specified the corresponding replacement data set, NEWCKPTn={{(DSName=,VOLser=)}(STRNAME=)}, either on the:

- CKPTDEF initialization statement (only during a cold start) or
- \$T CKPTDEF command.

and it has not already been used, you can copy the appropriate in-storage checkpoint (CKPT1 or CKPT2) to the corresponding NEWCKPTn data set. Respond to the \$HASP271 CHECKPOINT RECONFIGURATION OPTIONS and \$HASP272 ENTER RESPONSE message pair with the appropriate "FORWARD" option (that is, a reply of '1' or '2').

The time you and JES2 are involved in a checkpoint reconfiguration dialog is time that the checkpoint is unavailable to the JES2 members. It is important to minimize this length of time if possible and understand how to best consolidate \$T commands. Use a single `$T CKPTDEF,NEWCKPTn=(...),RECONFIG=YES` outside a reconfiguration to speed reconfiguration processing. Specifying NEWCKPTn and RECONFIG=YES on the same command eliminates any ambiguity to JES2 whenever multiple NEWCKPTn specifications are entered on different JES2 members within the same checkpoint cycle.

If you have not previously defined the corresponding replacement data set, or it has already been used, you can define it by responding `CKPTDEF NEWCKPTn=({DSN=dsname,VOL=volser})|(STRNAME=strname)}` to the \$HASP271 CHECKPOINT RECONFIGURATION OPTIONS and \$HASP272 ENTER RESPONSE message pair. JES2 will then reissue messages \$HASP271 and \$HASP272 so that you can copy the in-storage checkpoint as described above.

Discontinue Using a Checkpoint Data Set

If you want to discontinue using a checkpoint data set, respond to the \$HASP271 CHECKPOINT RECONFIGURATION OPTIONS and \$HASP272 ENTER RESPONSE message pair with the appropriate "SUSPEND" option (that is, a reply of '5' or '6').

Note: If your MAS is running in DUPLEX mode and one of more members specified DUPLEX=OFF, you can still specify discontinue using CKPT1. JES2 will attempt to make CKPT2 your primary data set. After JES2 completes SUSPEND processing, DUPLEX=ON is set for every MAS member.

Example Operator-initiated Reconfiguration Dialog

The following example illustrates a typical console sequence when an operator initiates the checkpoint reconfiguration dialog. The original checkpoint configuration as defined in the JES2 initialization data set is:

```
CKPTDEF CKPT1=(DSN=SYS1.JES2CKPT1,VOL=CHECK1,INUSE=YES),
        CKPT2=(DSN=SYS1.JES2CKPT2,VOL=CHECK2,INUSE=YES),
        NEWCKPT1=(DSN=SYS1.JES2REP1,VOL=CHECK3),
        NEWCKPT2=(DSN=SYS1.JES2REP2,VOL=CHECK4),
        MODE=DUAL
```

Assume that during a previous checkpoint reconfiguration, CKPT1 was forwarded to NEWCKPT1 on volume CHECK3. If you issue a `$D CKPTDEF` command, JES2 displays the following current checkpoint definition:

```
CKPTDEF CKPT1=(DSN=SYS1.JES2REP1,VOL=CHECK3,INUSE=YES),
        CKPT2=(DSN=SYS1.JES2CKPT2,VOL=CHECK2,INUSE=YES),
        NEWCKPT1=(DSN=,VOL=),
        NEWCKPT2=(DSN=SYS1.JES2REP2,VOL=CHECK4),
        MODE=DUAL
```

To begin a checkpoint reconfiguration dialog and return CKPT1 to its original definition:

1. Enter
`$T CKPTDEF,NEWCKPT1=(DSN=SYS1.JES2CKPT1,VOL=CHECK1),RECONFIG=YES`
2. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTING
3. \$HASP233 REASON FOR JES2 CHECKPOINT RECONFIGURATION IS OPERATOR REQUEST
4. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTED - DRIVEN BY MEMBER SY4

5. \$HASP271 CHECKPOINT RECONFIGURATION OPTIONS...VALID RESPONSES ARE...
6. \$HASP272 ENTER RESPONSE
7. Operator response: R nn,1
8. \$HASP273 JES2 CKPT1 DATA SET WILL BE ASSIGNED TO NEWCKPT1 ...
9. \$HASP272 ENTER RESPONSE
10. Operator response: R nn,CONT
11. \$HASP256 FUTURE AUTOMATIC FORWARDING OF CKPT1 IS SUSPENDED UNTIL NEWCKPT1 IS RESPECIFIED. ISSUE \$T CKPTDEF,NEWCKPT1=(...) TO RESPECIFY
In this example, \$HASP256 is a highlighted message and remains on the screen until you issue \$T CKPTDEF,NEWCKPT1=(...) in step 13.
12. \$HASP255 JES2 CHECKPOINT RECONFIGURATION COMPLETE
13. Enter
\$T CKPTDEF,NEWCKPT1=(...)

Checkpoint Reconfiguration Recovery

The JES2 checkpoint reconfiguration provides its own recovery for the following:

- Driving member failure - JES2 selects a new driving member and re-synchronizes reconfiguration processing
- JES2 member failure - an unrecoverable error occurs during reconfiguration processing - JES2 prompts the operator to create an emergency copy of the checkpoint before terminating
- Initiating member(s) failed in start-up processing - JES2 cancels the reconfiguration
- Reconfiguration delayed - a member fails to respond as requested by the driving member - JES2 issues \$HASP257

Driving Member Failure

The driving member fails and JES2 selects a new driving member. If successive members fail during a checkpoint reconfiguration, be aware that each new driver contains a less current in-storage copy of the checkpoint than the previous driver(s). Depending on how many driving members failed and how tolerant your operations are to down-level data, you might consider terminating all JES2 members and using the SYS1.EMERGENCY.HASPCCKPT you created in response to \$HASP279 on the original driver.

It is possible, that once JES2 selects a member to be the driving member for a checkpoint reconfiguration, that driving member then fails. JES2 then selects another driving member to take its place. JES2 issues \$HASP285 JES2 CHECKPOINT RECONFIGURATION RE-SYNCHRONIZING - DRIVEN BY MEMBER *member-name* to indicate that a new member has been selected as the new driving member. No operator involvement is required for the selection of the new driver. However, whenever a driving member fails, JES2 involves the operator for the remainder of the reconfiguration regardless of your OPVERIFY= specification.

Recovery from JES2 Member Failures

If a JES2 member experiences an unrecoverable error during the reconfiguration dialog, or if you reply 'TERM' to a dialog message while processing an I/O error, JES2 attempts to create an emergency copy of the checkpoint data set. JES2 then issues message \$HASP279 SPECIFY EMERGENCY CKPT VOLUME SERIAL OR '*NONE*' to which you can specify a volume on which to place this data set. (JES2

can only create an emergency data set on DASD.) If JES2 is successful, JES2 names this data set SYS1.EMERGNCY.HASPCKPT. You then receive message \$HASP274 SYS1.EMERGNCY.HASPCKPT CREATED ON VOLUME *volser* prior to JES2 termination. This data set can then be used when restarting JES2 on an all-member warm start.

When you respond to \$HASP279 requesting that JES2 create an emergency checkpoint, IBM recommends that you minimally create an emergency checkpoint from the driving member(s).

Initiating Member(s) Failure in Start-up Processing

If JES2 cannot determine the reason for the reconfiguration, such as if a member requests a reconfiguration and then fails during reconfiguration start-up processing, JES2 will not be able to determine the reason for the request. JES2 then cancels the reconfiguration and issues \$HASP255 JES2 CHECKPOINT RECONFIGURATION CANCELLED BY JES2.

If this type error occurs, simply restart the failing member. Unless there was a need to reconfigure the checkpoint as indicated by further messages from other members, the problem is cleared up by the restart alone.

Member Delayed

JES2 issues message

```
$HASP257 MEMBER delayed-member-name -- JES2 CHECKPOINT
RECONFIGURATION DELAYED BY MEMBER causing-member-name.
delayed-member-name IS WAITING FOR ACTION=action-code,
action-text
```

to provide an indication of which system member is experiencing problems. If this message is issued due to a temporary delay, JES2 deletes the message, and no operator action is required. However, the message might indicate a more serious problem indicating your need to fail the indicated system. Based on the set of \$HASP257 messages that you receive and their explanations, you might be able to diagnose the checkpoint reconfiguration problem(s). Refer to *z/OS JES2 Messages* for the message text that this message can issue and a detailed explanation for each.

Clean-up After a Checkpoint Reconfiguration

Once you have completed a reconfiguration dialog or JES2 has completed a checkpoint reconfiguration, you may want to:

- Return your checkpoint definitions to those typically used within your installation.
- Restart JES2 from an emergency checkpoint.
- Make the new checkpoint data set definitions permanent.

Returning to Your Typical Checkpoint Data Set Definitions

If you need to return your checkpoint data set definitions to the specifications as defined in your initialization data set, enter a reconfiguration dialog on any member by using the \$T CKPTDEF,NEWCKPTn=(...),RECONFIG=YES command. You can then reassign the replacement checkpoint (NEWCKPTn) data set to your original checkpoint definition and forward the primary (CKPTn) data set to the NEWCKPTn data set.

Although this reconfiguration process can be accomplished a number of different ways, IBM recommends the method used in the “Example Operator-initiated

Reconfiguration Dialog” on page 239 because it minimizes the time that the checkpoint data set is unavailable compared to other methods of redefining NEWCKPTn.

If the new configuration is sufficient and causing no system performance or availability problems, you can perform a reconfiguration at your convenience or not at all.

Restarting JES2 from an Emergency Checkpoint

If your checkpoint reconfiguration did not complete successfully, and you are unable to restart JES2 from your checkpoint, perform an all-member warm start using an emergency checkpoint data set. If in response to \$HASP279 issued by several members, you have created several emergency checkpoints, attempt to restart JES2 with an available emergency checkpoint that you select in the following order:

1. Original driving member
2. Subsequent driving member (if a previous driving member failed)
3. Other available emergency checkpoint.

Follow this example reconfiguration dialog when warm starting JES2 at initialization. This example assumes you are capable of returning to the original checkpoint DASD specifications below.

```
CKPTDEF CKPT1=(DSN=SYS1.JES2CKPT1,VOL=CHECK1,INUSE=YES),
        CKPT2=(DSN=SYS1.JES2CKPT2,VOL=CHECK2,INUSE=YES),
        NEWCKPT1=(DSN=SYS1.JES2REP1,VOL=CHECK3),
        NEWCKPT2=(DSN=SYS1.JES2REP2,VOL=CHECK4),
        MODE=DUAL,OPVERIFY=YES
```

Perform an all-member warm start and enter a reconfiguration dialog as follows:

1. enter

```
S JES2,PARM='WARM,RECONFIG'
```

JES2 initialization processing continues...

2. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTED - JES2 INITIALIZATION

3. \$HASP289 CKPT1 AND/OR CKPT2 SPECIFICATIONS ARE REQUIRED... VALID RESPONSES ARE...

4. \$HASP272 ENTER RESPONSE

5. Operator response:

```
R nn,CKPTDEF CKPT1=(DSN=SYS1.EMERGNCY.HASPCKPT,VOL=SP00L1,INUSE=YES),CKPT2=INUSE=NO
```

6. JES2 displays the original CKPTDEF statement with changes made in the previous step:

```
$HASP829 CKPTDEF CKPT1=(DSN=SYS1.EMERGNCY.HASPCKPT,VOL=SP00L1,INUSE=YES),
$HASP829 CKPT2=(DSN=SYS1.JES2CKPT2,VOL=CHECK2,INUSE=NO),
$HASP829 NEWCKPT1=(DSN=SYS1.JES2REP1,VOL=CHECK3),
$HASP829 NEWCKPT2=(DSN=SYS1.JES2REP2,VOL=CHECK4),
$HASP829 MODE=DUAL,OPVERIFY=YES
```

7. \$HASP289 CKPT1 AND/OR CKPT2 SPECIFICATIONS ARE REQUIRED... VALID RESPONSES ARE...

8. \$HASP272 ENTER RESPONSE

9. Operator response: R nn,END

At this point, you are using the emergency checkpoint only. Continue reconfiguration processing as in the following examples to achieve the desired permanent checkpoint configuration.

1. Enter

- ```
$T CKPTDEF,NEWCKPT1=(DSN=SYS1.JES2CKPT1,VOL=CHECK1),RECONFIG=YES
```
2. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTING
  3. \$HASP233 REASON FOR JES2 CHECKPOINT RECONFIGURATION IS OPERATOR REQUEST
  4. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTED - DRIVEN BY MEMBER SY5
  5. \$HASP271 CHECKPOINT RECONFIGURATION OPTIONS...VALID RESPONSES ARE...
  6. \$HASP272 ENTER RESPONSE
  7. Operator response: R nn,1
  8. \$HASP273 JES2 CKPT1 DATA SET WILL BE ASSIGNED TO NEWCKPT1 ...
  9. \$HASP272 ENTER RESPONSE
  10. Operator response: R nn,CONT
  11. \$HASP256 FUTURE AUTOMATIC FORWARDING OF CKPT2 IS SUSPENDED UNTIL NEWCKPT2 IS RESPECIFIED. ISSUE \$T CKPTDEF,NEWCKPT2=(...) TO RESPECIFY  
In this example, \$HASP256 is a highlighted message and remains on the screen until you issue \$T CKPTDEF,NEWCKPT2=(...) in step 13.
  12. \$HASP255 JES2 CHECKPOINT RECONFIGURATION COMPLETE
  13. Enter  
\$T CKPTDEF,NEWCKPT1=(DSN=SYS1.JES2REP1,VOL=CHECK3)

At this point, you have returned CKPT1 and NEWCKPT1 to their original definitions. The last task is to return CKPT2 and NEWCKPT2 to their original definitions as well.

1. Enter  
\$T CKPTDEF,RECONFIG=YES
2. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTING
3. \$HASP233 REASON FOR JES2 CHECKPOINT RECONFIGURATION IS OPERATOR REQUEST
4. \$HASP285 JES2 CHECKPOINT RECONFIGURATION STARTED - DRIVEN BY MEMBER SY3
5. \$HASP271 CHECKPOINT RECONFIGURATION OPTIONS...VALID RESPONSES ARE...
6. \$HASP272 ENTER RESPONSE
7. Operator response: R nn,8
8. \$HASP273 JES2 CKPT2 DATA SET WILL BE ASSIGNED ...
9. \$HASP272 ENTER RESPONSE
10. Operator response: R nn,CONT
11. \$HASP255 JES2 CHECKPOINT RECONFIGURATION COMPLETE

At this point, you have resumed using CKPT2. NEWCKPT2 is left unchanged as originally specified. We have now returned all checkpoint specifications to their original definitions.

### **Making the Checkpoint Reconfiguration Definitions Permanent**

JES2 honors the checkpoint configuration definition across any JES2 restart and forwards data sets based on the CKPTn and NEWCKPTn definitions. However, for consistency between your initialization data set and the new checkpoint definitions, you should update your initialization data set as soon as possible.

During JES2 checkpoint reconfiguration processing, JES2 tries to add a pointer in each replaced checkpoint data set to provide a 'forwarding trail'. (Refer to "Using the NEWCKPTn Data Sets" on page 225 for a discussion of JES2 checkpoint data set forwarding.) You cannot delete this series of old checkpoint data sets until you have updated your initialization data set to point to your current checkpoint. If JES2 was unable to write the forwarding information into the old checkpoint (possibly caused by an I/O error) you should update the CKPTDEF statement in all your initialization data sets as soon as possible. This effectively makes your current checkpoint definition permanent and eliminates the forwarding trail. Otherwise, whenever you warm start JES2, JES2 will enter a reconfiguration dialog at initialization.

**Attention:** If, on a JES2 restart, you specify RECONFIG as an option in response to the \$HASP426 SPECIFY OPTIONS message or you have previously added RECONFIG on an S JES2 command, JES2 will ignore all checkpoint data set forwarding previously defined. JES2 will override all forwarding and use the checkpoint data set you specified from the console. If this is inappropriate to your restart situation, be certain to have either redefined your checkpoint data sets in your initialization data set or **do not** use the RECONFIG option. Refer to "Specifying the Start Options" on page 27 for information on specifying JES2 start options and *z/OS MVS JCL Reference* for specifying the JES2 PROC statement.

## Moving a JES2 Checkpoint to a Coupling Facility Using System Managed Rebuild

Managing a JES2 checkpoint in a coupling facility is different from managing a JES2 checkpoint on DASD. The main difference is coupling facilities store data in temporary memory versus the permanent storage of a DASD. The data JES2 stores in a coupling facility is needed for JES2 restart. If CKPT2 is placed on DASD, it can be used by JES2 restart processing if the data in the coupling facility is lost. However, if both checkpoints are on coupling facilities and the coupling facility data is lost (for example due to an extended power outage), then JES2 must be cold started, resulting in the loss of all Jobs and SYSOUT in the JES2 work queues. Because of this, special care must be taken with any coupling facility that contains a JES2 checkpoint structure.

In general, to prevent a total loss of the job queue, you should use 2 checkpoints, specify CKPT DUPLEX=ON on all members, and place CKPT2 on a DASD. You can also use nonvolatile coupling facilities (with battery backup in case of power failure) to minimize the impact of a power failure. However, data on a coupling facility can be lost in ways other than a power failure. The most common way JES2 checkpoints structures in a coupling facility are lost is when the coupling facilities are reinitialized while JES2 structures are still active in them. To prevent this, the JES2 structures should be moved out of a coupling facility prior to reinitializing it. Depending on the availability of an alternate coupling facility, this can be done in one of two ways.

If there are no suitable coupling facilities available to hold the checkpoint data set, or if this is a planned extended power outage, then the checkpoint data set should be moved to a DASD. This can be done by an operator initiated checkpoint reconfiguration. See "Operator-initiated Entrance into a Checkpoint Reconfiguration Dialog" on page 238 for details on how to do this.

If there is a suitable alternative coupling facility available, then a system managed rebuild can be used to move the checkpoint structure to the new coupling facility. To accomplish this do the following:

1. Ensure system managed processes are enabled in your SYSPLEX. See "System-Managed Processes Considerations" in *z/OS MVS Setting Up a Sysplex* for a complete list of the requirements.
2. Ensure that the structure definitions for the JES2 checkpoint data sets in the active CFRM policy will direct the checkpoint data set to a suitable coupling facility. If not, update and activate the appropriate policy.
3. Use the appropriate XCF command to either rebuild only the JES2 checkpoint structure (SETXCF START,REBUILD,STRNAME=) or all structures on a coupling facility (SETXCF START,REBUILD,CFNAME=).
4. Once the rebuild completes, use the D XCF,STRUCTURE,STRNAME= to display the checkpoint structure and verify it is now on a suitable structure.

During the rebuild process, you may notice that JES2 is not responding to commands and not starting new work. Other MAS members may issue messages about not being able to access the checkpoint. JES2 will return to normal operations once the rebuild completes. To minimize the time required to complete the rebuild, you can request the JES2 structures be rebuilt individually by using the SETXCF START,REBUILD,STRNAME= instead of specifying CFNAME=. Alternatively, the structures can be rebuilt when JES2 is not active.

**Note:** JES2 supports rebuild of its structures only for the SETXCF START,REBUILD command. In the event of any other failure of the coupling facility (such as loss of connectivity), the I/O form of checkpoint reconfiguration will be used for recovery.

---

## Recovering from Member Failures on Other JES2 Members

In a JES2 MAS, when a JES2 member fails, recovery depends on whether the checkpoint data set(s) reside on a coupling facility structure or on a DASD volume, and whether the failing member involves only the JES2 member or involves MVS.

### Checkpoint on DASD

- If only the JES2 member fails, and it holds the lock of a checkpoint data set that resides on DASD, recovery requires releasing the software checkpoint lock to make the checkpoint data set available to other JES2 members in the MAS.
- If MVS fails (which includes the JES2 member with a checkpoint data set residing on DASD), jobs executing on that member must be requeued before another JES2 member can restart those jobs. To make jobs eligible for restart:
  - The hardware lock holding the checkpoint data set must be reset if it is held.
  - The software checkpoint lock must be reset if it is held by the failed JES2 member.
  - The jobs that were executing on the failed member must be requeued for processing.

### Checkpoint on Coupling Facility Structure

If a JES2 member fails and the checkpoint data resides on a coupling facility structure, the coupling facility lock that JES2 uses to control access to the checkpoint is released automatically. However, an installation still must requeue jobs that had been executing on the failed member so they can be selected for execution on an active member.

You can recover from a member failure through use of operator commands or, in a sysplex, through use of the AUTOEMEM option.

## Using Operator Commands

When using commands to requeue the jobs of a failed member, an operator must first determine whether the failure involves only the JES2 member or involves the MVS system. Also, if the checkpoint data set resides on a DASD volume, the operator has to determine if checkpoint locks are held and reset them before requeuing the jobs.

### JES2 Failure Only

If the failed member (JES2 member) holds the JES2 checkpoint data set, the operator must:

1. Reset the software checkpoint lock (if the checkpoint is on DASD) so other JES2 members of the MAS can access it. Use the `$E CKPTLOCK,HELDDBY=` command to reset the lock.
2. Restart the failed JES2 member through a hot start.

If the JES2 checkpoint data set is not held, the operator only restarts JES2 to provide JES2 services to the jobs executing under MVS.

### MVS and JES2 Failure

If the failed member holds the JES2 checkpoint data set, the operator must:

1. If the checkpoint resides on DASD, reset the hardware lock if held (as indicated by message `$HASP263`).
2. If the checkpoint resides on DASD, reset the software checkpoint lock by using the `$E CKPTLOCK,HELDDBY=` command.
3. Requeue the jobs for restart by entering the `$E MEMBER` command, which makes jobs eligible for restart on another JES2 member. Note that jobs with member affinity to the failed system will not be restarted until the failed member is available or member affinity for those jobs is modified.

Figure 44 on page 247 shows a sequence of events in a 2-member MAS configuration where the software checkpoint lock is held by the failed JES2 member (SYSA). The operator must respond to the `$HASP263` message by entering the `$E CKPTLOCK,HELDDBY=` command, even though the MVS system (SYSTEMA) continues to process jobs.




Figure 44. Two-Member MAS with JES2 Failure (Checkpoint on DASD)

In a 2-member MAS configuration where the checkpoint resides on a coupling facility structure and the coupling facility lock that JES2 uses to control access to the checkpoint was held by the failed JES2 member (SYSA), the operator does not have to release it; the coupling facility lock is released without operator intervention while the MVS system (SYSTEMA) continues to process jobs.

Note that the \$HASP263 message contains a modified text that is informational.




Figure 45. Two-Member MAS with JES2 Failure (Checkpoint on Coupling Facility)

Figure 46 on page 248 shows a sequence of events in a 2-member MAS configuration where the checkpoint data set resides on DASD and both the hardware lock and the software checkpoint lock are held by the failed JES2 member (SYSA). In this instance, both the JES2 member and the MVS system (SYSTEMA) have failed.




Figure 46. Two-Member MAS with JES2 and MVS Failure (DASD)

## Using the AUTOEMEM Option

IBM recommends that multiple JES2 members in the same sysplex use the AUTOEMEM option. The AUTOEMEM option makes jobs eligible for restart if another JES2 member (MVS and JES2) in a sysplex has failed.

The AUTOEMEM option has no effect on the DASD hardware lock. If it is held by a failed member, the operator must reset the lock.

The AUTOEMEM option has no effect on the coupling facility lock, because that lock is released automatically when the JES2 address space ends.

Through the MASDEF initialization statement, you indicate whether:

- A JES2 member can have other members make its jobs eligible for restart if it fails (by specifying AUTOEMEM=ON).

- A JES2 member can make jobs from any other failed member eligible for restart (by specifying RESTART=YES).
- A JES2 member can have other members make its jobs eligible for restart, but **not** allow this member to make jobs from any other failed member eligible for restart (by specifying AUTOEMEM=ON and RESTART=NO).

**Note:** If all members specify RESTART=NO, no jobs can be made eligible for restart automatically.

If only the JES2 member fails, the operator must restart the JES2 member so it can provide services for the jobs that continue to execute on the active MVS system.

As shown in Figure 47 and Figure 49 on page 251, JES2 uses the cross-system coupling facility (XCF) to communicate status among JES2 members in a sysplex. When a participating MVS system fails, other JES2 members are notified through XCF. When a JES2 member fails, other JES2 members are notified through XCF. For information about XCF and the sysplex, see *z/OS MVS Setting Up a Sysplex*.

Figure 47 shows a sequence of events in a 2-member MAS configuration where the checkpoint resides on DASD, the software checkpoint lock is held by the failed JES2 member (SYSA), and the AUTOEMEM option is enabled. In this instance, only the JES2 member has failed; the MVS system (SYSTEMA) continues to process jobs. Note that the \$HASP784 message appears in the SYSLOG only.




Figure 47. Sysplex with the AUTOEMEM Option Enabled, a JES2 Failure (DASD)

Figure 48 on page 250 shows a sequence of events in a 2-member MAS configuration where the checkpoint resides on a coupling facility structure, the coupling facility lock that JES2 uses to control access to the checkpoint is held by



the failed JES2 member (SYSA), and the AUTOEMEM option is enabled. In this instance, only the JES2 member has failed; the MVS system (SYSTEMA) continues to process jobs. The coupling facility lock is released from SYSA and passed to the next waiting member of the queue. Note that the \$HASP784 message appears in the SYSLOG only.





Figure 48. Sysplex with the AUTOEMEM Option Enabled, a JES2 Failure (Coupling Facility)

Figure 49 on page 251 shows a sequence of events in a 2-member MAS configuration where the hardware lock and the software checkpoint lock are held by the failed JES2 member (SYSA), the MVS system (SYSTEMA) has failed, and the AUTOEMEM option is enabled. Note that the \$HASP784 message appears in the SYSLOG only.



On SYSTEMA:

SYSTEMA Fails  
(For example, the  
system failed  
and entered  
a nonrestartable  
wait state.)

On SYSTEMB:

```
$HASP263 WAITING FOR ACCESS
 TO JES2 CHECKPOINT VOLUME...
```

#### **SYSTEM RESET** (Operator)

```
$HASP264 WAITING FOR RELEASE
 OF CKPT LOCK BY SYSA
```

```
IXC402D SYSTEMA LAST OPERATIVE
 AT hh:mm:ss ...
 REPLY DOWN IF MVS IS DOWN ...
```

#### **R nn,DOWN**

```
$HASP784 ATTEMPTING AUTOMATIC RESET
 OF JES2 MEMBER SYSA
(JES2 automatically resets checkpoint lock)
```

```
$HASP493 SYSB MEMBER SYSA RESTART IS
 IN PROGRESS
 (JES2 automatically makes jobs
 eligible for restart)
```

```
$HASP492 SYSB MEMBER SYSA RESTART
 HAS COMPLETED
```

Re-IPL SYSTEMA

Figure 49. Sysplex with the AUTOEMEM Option Enabled, an MVS System Failure

## Enabling the JES2 AUTOEMEM Option at Initialization

IBM recommends that each member enable the AUTOEMEM option (AUTOEMEM=ON on the MASDEF initialization statement), however, if you use

automatic restart management to restart batch jobs and started tasks, automatic restart management can restart jobs regardless of whether the AUTOEMEM option is enabled.

The following scenario and figure show a sample configuration enabled for the AUTOEMEM option. The configuration consists of two JES2 members in the same sysplex. In the 2-member sysplex (SYSPLEX1), the AUTOEMEM option is enabled for both members. For information on configuring a sysplex, see *z/OS MVS Setting Up a Sysplex*.

Enable the AUTOEMEM option by coding JES2 MASDEF initialization statements on the JES2 members in SYSPLEX1. The following two MASDEF initialization statements enable the option:

MVSa: MASDEF AUTOEMEM=ON,RESTART=YES,OWNMEMB=HAS1, ...

MVSb: MASDEF AUTOEMEM=ON,RESTART=YES,OWNMEMB=HAS2, ...




Figure 50. The JES2 AUTOEMEM Option in a Two-Member Sysplex Configuration

## Providing Copies of the JES2 Checkpoint to Application Programs

Certain authorized applications have a need to read information in the checkpoint data set. JES2 meets that need by maintaining and periodically updating a copy of the checkpoint data set. When an application requests checkpoint data by using the subsystem interface request macro (IEFSSREQ), JES2 makes the most recent copy of a subset of the checkpoint data set available to the requesting application.

To ensure that the copy of the checkpoint data set remains constant while the application is working with it, JES2 does not make updates to this copy until the application releases the copy.

If another application then requests checkpoint data, JES2 determines if the copy being used is the latest copy. If it is, JES2 makes this copy available to the second application. (So, multiple applications can use the same copy of the checkpoint data set, and the copy exists until the last user accessing the data releases the copy.) If the copy being used by the first application is not the latest copy, JES2 will give the application access to the latest copy.

JES2 controls the maximum number of copies that can exist at one time. JES2 will not create a new copy if the number of copies in use is equal to that maximum, but will make the most recently created copy available to the application. However, the copy might not contain the most current information, because it was not recently updated. Therefore, to avoid obtaining outdated information, applications should obtain whatever information they require and release the version as quickly as possible.

JES2 will determine an appropriate maximum number of versions at initialization. The installation can, however, control the copies made available by providing input on the VERSIONS= parameter on the CKPTDEF initialization statement. For information about the IEFSSREQ macro, see *z/OS MVS Using the Subsystem Interface*.

## **Using Versions= to Provide Copies of the Checkpoint Data Set for Use by Applications**

Use the VERSIONS= parameter on the CKPTDEF initialization statement to specify the maximum number of copies, or versions, of the checkpoint data set JES2 can create. This method of providing copies of the checkpoint data set is similar to allowing JES2 to manage the copies, except that the installation explicitly specifies the maximum number of copies that can exist at one time.



---

## Part 5. Network Job Entry (NJE)

|                                                        |     |
|--------------------------------------------------------|-----|
| <b>Chapter 5. Network Job Entry (NJE)</b>              | 257 |
| Overview of NJE                                        | 257 |
| BSC Versus SNA                                         | 257 |
| BSC                                                    | 257 |
| SNA                                                    | 257 |
| Logical and Physical Configurations                    | 258 |
| Hardware Considerations for NJE                        | 258 |
| Data Flow Through a Network                            | 259 |
| How the Network Processes Jobs, Commands, and Messages | 260 |
| How JES2 Processes Jobs from TSO/E User ID in NJE      | 260 |
| How the Network Determines the Execution Node          | 261 |
| How the Network Transmits Input Jobs and SYSOUT        | 261 |
| Assignment of JES2 Job Identifiers                     | 262 |
| Determining the Destination of Output                  | 263 |
| Designing the Network                                  | 264 |
| General Considerations                                 | 264 |
| Network Topology                                       | 264 |
| Performance                                            | 264 |
| Security                                               | 264 |
| Node Names                                             | 265 |
| Resistance                                             | 265 |
| Network Topology                                       | 265 |
| Simple Configurations                                  | 265 |
| Complex Configurations                                 | 266 |
| Performance Considerations                             | 268 |
| Compression                                            | 268 |
| Compaction                                             | 268 |
| Security Considerations                                | 269 |
| Password Processing                                    | 269 |
| Encryption                                             | 269 |
| Initializing the Network Job Entry Functions           | 270 |
| Initialization Statements                              | 270 |
| Naming the Nodes in a Network                          | 271 |
| Default Names                                          | 271 |
| Naming Restrictions                                    | 271 |
| Symbolic Node Names                                    | 271 |
| Defining Nodes Using Generics                          | 272 |
| Specifying Multiple Passwords for NJE Connections      | 273 |
| Using Destination Identifiers (DESTIDs)                | 273 |
| Defining a Minimum Configuration for BSC NJE           | 274 |
| NODENUM                                                | 275 |
| LINENUM                                                | 275 |
| OWNNODE                                                | 275 |
| Default NJE Parameters (BSC and SNA)                   | 275 |
| Sending and Receiving Jobs and SYSOUT                  | 276 |
| Controlling Jobs Looping in the Network                | 278 |
| Routing Output                                         | 278 |
| Command Authority                                      | 278 |
| Network Time Tolerance                                 | 279 |
| Using Different Operating Systems in a Network         | 279 |
| Execution Node Considerations                          | 279 |
| Output Node Considerations                             | 280 |
| Defining a Minimum Configuration for SNA NJE           | 281 |

|                                                                       |     |
|-----------------------------------------------------------------------|-----|
| Special Considerations for SNA NJE Networking . . . . .               | 283 |
| Multiple Parallel SNA NJE Sessions Between Two Nodes. . . . .         | 284 |
| VTAM Definitions for SNA NJE . . . . .                                | 285 |
| VTAM APPL Statement . . . . .                                         | 285 |
| NJE Bind Image . . . . .                                              | 285 |
| SNA Buffer Size . . . . .                                             | 286 |
| Specifying Unique Log Mode Table Entries for Specific SNA Connections | 287 |
| Displaying Information About a Network . . . . .                      | 287 |
| Displaying NJE Global Parameters . . . . .                            | 288 |
| Displaying Node Attributes . . . . .                                  | 288 |
| Displaying JES2 Applications for SNA NJE . . . . .                    | 288 |
| Display Symbolic Destination Identifiers . . . . .                    | 288 |
| Displaying Active Paths in a Network . . . . .                        | 289 |
| Displaying NJE Connections . . . . .                                  | 289 |
| Sending a Display Command . . . . .                                   | 290 |
| Connecting the Network . . . . .                                      | 290 |
| Starting BSC Dynamic Connections. . . . .                             | 291 |
| Starting SNA Dynamic Connections. . . . .                             | 291 |
| SMF Record Summary: NJE (Network Job Entry) Processing . . . . .      | 291 |
| The Path Manager . . . . .                                            | 291 |
| Network Connection Control Records . . . . .                          | 292 |
| Non-Path Manager Connections . . . . .                                | 292 |
| Private Connections . . . . .                                         | 294 |
| Summary of PATHMGR=and PRIVATE=Parameters . . . . .                   | 294 |
| Static Connections . . . . .                                          | 295 |
| Using the CONNECT Statement . . . . .                                 | 296 |
| Controlling Static Connections. . . . .                               | 297 |
| Preventing Looping When Using Connect Statements . . . . .            | 297 |
| Defining and Communicating Between Subnets . . . . .                  | 299 |
| Determining Path Resistance . . . . .                                 | 301 |
| Calculating Resistance for Adjacent Connections . . . . .             | 301 |
| Calculating Resistance for Non-Adjacent Nodes . . . . .               | 304 |
| Controlling Store-and-Forward Transmissions . . . . .                 | 305 |
| Path Selection Considerations. . . . .                                | 305 |
| PATH . . . . .                                                        | 306 |
| RESTTOL . . . . .                                                     | 306 |
| RESTMAX . . . . .                                                     | 306 |
| Extending Network Capability . . . . .                                | 306 |
| Adding a Node to an Existing Network. . . . .                         | 309 |
| Multi-Access Spool Configuration Considerations for NJE. . . . .      | 309 |
| Example of a Multi-Access Spool Node . . . . .                        | 310 |
| Processing When WASHDC is a Version 5 Node . . . . .                  | 310 |
| Processing When WASHDC is a Pre-Version 5 Node . . . . .              | 310 |
| Queueing Messages to a Multi-Access Spool Node . . . . .              | 311 |
| MASDEF Queueing Parameters . . . . .                                  | 311 |
| NJEDEF Queueing Parameter. . . . .                                    | 312 |
| Defining a Multi-Access Spool Node (SNA Considerations) . . . . .     | 312 |



---

## Chapter 5. Network Job Entry (NJE)

This chapter presents an overview of an NJE network, how to design a network, and how to connect a network. This chapter also discusses initializing NJE functions in a JES2 environment for various configurations and defining a multi-access spool node.

*NJE Installation* explains these concepts in greater detail.

---

### Overview of NJE

Geographically dispersed processors communicate using the network job entry (NJE) facility for the purpose of transmitting commands, messages, jobs, and job output between the host systems (AS/400\*, JES2, JES3, VM/RSCS, and VSE/POWER). The facility can also provide communication among processors at the same location as an alternative to a JES2 multi-access spool configuration. An NJE network can consist of up to 32,767 nodes. Each of the nodes may be either a single processor or a multi-access spool (MAS) configuration. A MAS configuration is one in which as many as 32 members share one set of JES2 spool and checkpoint volumes. NJE can also communicate between primary and secondary JES2 members on the same processor.

**NJE is compatible across all releases of AS/400, JES2, JES3, VM/RSCS, and VSE/POWER.**

### BSC Versus SNA

There are two ways to send and receive data in NJE. One is binary synchronous communication (BSC) and the other is Systems Network Architecture (SNA).

A network can consist of any combination of SNA and BSC connections. Each of these has its advantages. Your choice of which to use depends on the available hardware and software.

#### BSC

BSC is a form of line control that uses a standard set of control characters and control character sequences for transmission of binary coded data between systems in a network. A BSC node uses:

- Remote terminal access method (RTAM) execute channel programming (EXCP) and emulation program (EP) or partitioned emulation programming extension (PEP) in the communications controller
- Channel-to-channel (CTC) connections are identical to BSC communications except CTC connections do not use EP or PEP. CTC connections are best suited for connections to nodes within the same computer facility.

NJE protocols support an ESCON\* Basic Mode CTC (defined to the hardware configuration dialog as BCTC) and a 3088 CTC, but do not support an ESCON CTC (defined to the hardware configuration dialog as SCTC).

#### SNA

SNA is the description of logical structures, formats, protocols, and operational sequences, for transmitting information units through, and controlling the configuration of, networks. A SNA node uses:

- Virtual telecommunication access method (VTAM) to control the sessions between the nodes.

- The network control program (NCP) or partitioned emulation programming (PEP) extension to control lines.

## Logical and Physical Configurations

The difference between logical and physical configurations is the most significant distinction between SNA and BSC protocols. In BSC NJE, these configurations are similar. In SNA NJE, the logical and physical configurations can be quite different. Various routing tables in the host and the communication controllers determine the logical configuration.

In Figure 51, Node A can have a direct session with Node C even though no direct line exists between them. Node A and Node C view themselves as being directly connected to each other. ACF/VTAM<sup>®</sup> and Multi-Systems Networking Facility (MSNF) support this connection through the communications controllers (cc) and the network control programs (NCP), which are transparent to the nodes. Figure 51 represents a simple SNA NJE configuration.




Figure 51. Simple SNA NJE Configuration

## Hardware Considerations for NJE

BSC lines, channel-to-channel (CTC) adapters, or SNA network lines connect JES2 systems participating in an NJE environment.

BSC lines attached to IBM 3704, 3705, or 3725 Communication Controllers operate in emulation mode. Generate NJE 3704s and 3705s to emulate a 2701 communication controller (see both *IBM 3704 and 3705 Communications Controllers* and *IBM 3725 Model 1 Communications Controller*).

During system installation, use hardware configuration definition (HCD) to define the attached NJE lines as follows:

- On the 'Primary Task Selection' panel, select '1. Define, modify, or view configuration'. On the resulting panel, select '5. I/O devices'
- On the 'Add Device' panel, specify the device type as BSC1.
- On the 'Define Parameter / Feature' panel, specify the TCU parameter as 2701

Refer to *z/OS HCD User's Guide* for a complete list of the steps involved in defining a device.

Channel-to-channel adapters supported as high-speed communication lines for NJE must be on block multiplexers because they can “lock up” selector channels. Use the LINE(nnnn) JES2 initialization statement to define these adapters. (See *z/OS JES2 Initialization and Tuning Reference* for details concerning the LINE(nnnn) parameters.) If you do not code these specifications and I/O errors occur when establishing the network, you might find it very difficult to analyze those errors. Connections using internal or external CTC devices only operate in 360 compatibility mode.

Use the following steps to add the control units and CTC:

Add the control units:

- Follow the steps as described in *z/OS HCD User's Guide*.
- On the ‘Add Control Unit’ panel (accessed from the ‘Select Processor / Control Unit’ panel), specify the ‘I/O concurrency level’ as 2. (This corresponds to SHARED=NO in I/O Configuration Program (IOCP) ).

Add the CTC:

- Use HCD and follow the steps as described in *z/OS HCD User's Guide*.  
On the ‘Define Parameter / Feature’ panel, specify Yes or No, as applicable, for the parameters shown. For ‘370’ specify Yes.
- Add UNIT=unit-addr to the JES2 LINE(nnnn) initialization statement.

Note that multiple systems through multiple CTCs on the same channel path could cause a deadlock condition.

You can also use CTC adapters to support an SNA NJE environment; however, ACF/VTAM controls these CTC adapters. Consult *z/OS Communications Server: SNA Resource Definition Reference* for VTAM-CTC requirements.

SNA NJE application-to-application sessions using SDLC lines require that the Advanced Communication Function (ACF) for the Network Control Program/VS (NCP/VS) or the partitioned emulator program (PEP) resides in the IBM 3705. Also, the processors participating in these sessions must have ACF for VTAM and the Multi-System Networking Facility VTAM installed.

Many parameters affect the performance of BSC NJE traffic on a channel-to-channel adapter. At times, increasing or decreasing buffer sizes can result in a decrease of performance because of varying channel loads, hardware limitations, and the speed of the CTC adapter itself. Experienced system programmers (with their system engineers) should tune JES2 parameters. While adjusting the parameters, carefully consider the effects of the following on performance:

- Teleprocessing (TP) buffer sizes
- The number of buffers per spool page
- The loads on the channel
- Other demands on the BSC processes (such as RJE devices).

## Data Flow Through a Network

You can enter a job on one node, route it to another node for execution, and send the output to one or more nodes for output. Figure 52 on page 262 illustrates the data flow and shows the JES2 devices that participate in the transmission, routing, and receipt of jobs.

To determine the SYSOUT classes for job output within your network, see “Output Class Assignment” on page 113. Coordination of SYSOUT is important for consistency of print and punch classes among the network nodes.

### **How the Network Processes Jobs, Commands, and Messages**

Jobs and associated in-stream data entering the network from a local input device, internal reader, or remote workstation can execute on the entry node or any other node in the network. The entry node queues jobs and in-stream data sets destined for another node. The target node must have the proper resources (for example, the necessary tape drives, direct-access devices, and specific data sets) and must be the job’s designated execution node. If you lose or change a path during work flow, the node currently processing the work will either hold the job or, when possible, select an alternate transmission path.

JES2 queues commands to a remote console processor for transmission to the command’s final destination. If JES2 loses the path to the final destination, JES2 attempts to return a diagnostic message to the entry console. Severe errors can cause JES2 to discard commands without issuing unique diagnostic messages.

Messages flow through the network like commands; however, JES2 discards messages if it loses the path to the final destination.

## **How JES2 Processes Jobs from TSO/E User ID in NJE**

When a job is first read in by JES2, the TSO/E user ID is stored in the job header record if NOTIFY= was specified on the job statement. The TSO/E user ID can differ from the RACF userid specified in USER= on the job statement. The originating node name is also stored in the job header.

If the job header contains a NOTIFY userid and the job is transmitted from its origin node for execution on another node, the job transmitter issues a message to the NOTIFY user ID indicating that the job was transmitted for execution.

When the job completes execution, the JES2 output processor on the execution node examines the NOTIFY user ID in the job header. If the NOTIFY userid is present, a notification message is issued and directed to the userid on the origin node. If the origin node and execution node are the same, the result is an issuance of an MVS SEND command specifying the userid. If the origin node and execution node are different, the notification is sent back to the origin node through the JES2 remote console processor and RTAM; the JES2 system on the origin node issues the SEND command.

When a job’s system output (or any part of it) reaches its ultimate destination, the SYSOUT receiver on the destination node examines the userid in the job header. If NOTIFY= was specified on the job card, the SYSOUT receiver issues a message to the specified user indicating that the job’s SYSOUT was received and where it was received. The message will be sent to the job’s origin node (as explained above for the end-of-execution message). For transmissions that entered the network through the TSO/Extensions interactive data transmission facility, NOTIFY= is automatically specified. For further discussion, see the “Other Programming Considerations” section of the description of Exit 13 in *z/OS JES2 Installation Exits*.

If an installation wants local TSO/E userids notified when mail is placed in the output queue (from either another node or a spool reload procedure), specify MAILMSG=YES on the NJEDEF initialization statement.

## How the Network Determines the Execution Node

At the system on which jobs are submitted, JES2 determines the execution node for a job in one of three ways:

- The job enters the system on a device that has a defined default execution node. You can define the default execution node by using the XEQDEST= parameter on RDR(nn) or R(nnnn).RD(m) initialization statements.
- A /\*XMIT, /\*XEQ, or /\*ROUTE XEQ control statement, in the JCL for the job, explicitly defines the execution node (overriding the default).
- An operator command (entered when the job is queued for execution or transmission to another node) explicitly defines the execution node (overriding the default or control statement routing).

## How the Network Transmits Input Jobs and SYSOUT

With NJE, JES2 can transmit a job intended to execute at another node directly to that node. If intermediate nodes are present, JES2 receives, spools, and retransmits the job through each of these. NJE handles job transmission on a store-and-forward basis. That is, a node must completely receive a job before it can take any action to either execute the job or transmit the job to another node. Once the receiving node has completely received and spooled the job, the transmitting node frees the resources that it allocated to transmit the job.

JES2 can send both job and SYSOUT output data sets through a series of devices called transmitters, which select files destined for nodes reachable through the NJE line to which these transmitters are assigned. Job and SYSOUT transmitters select files from the transmission (\$XMIT) and Network queues respectively, which are ordered FIFO (first-in-first-out) within priority. There can be multiple transmitters (and receivers) on a line as defined on the NJEDEF or LINE initialization statements. For recommendations on how to specify transmitters and receivers in your initialization stream, see “Specifying Transmitters and Receivers” on page 276.

SYSOUT files can range in size from very small (for example, one record, such as a Netmail acknowledgement) to very large (millions of records). Once a transmitter has selected a file, it will not interleave it with other files or voluntarily interrupt the transmission until that file is completely transmitted. If the line drops or the transmission is otherwise interrupted, the entire file must be re-transmitted from the beginning. For recommendations on how to set up transmitters to send SYSOUT files, see “Specifying Work Selection Values for NJE Transmitters” on page 277.




Figure 52. Processing Flow Through a Network

### Assignment of JES2 Job Identifiers

When a JES2 system transmits a job to another system, the receiving system attempts to assign the original job identifier (from the NJE job header) to the received job. The original job ID is used as long as the job number is not already assigned, and either the job number is inside the JOBDEF RANGE or

RASSIGN=YES. (The default is RASSIGN=YES.) Otherwise a new job ID is assigned from available job numbers within the JOBDEF RANGE. If this number is currently in use on the receiving system, the receiver will try to assign the next available job identifier. The newly assigned job identifier is not placed in the job header. The job header always contains the job identifier assigned at the node where the job originated. This job identifier assignment procedure is the same for both jobs and system output.

The input service processor, the job receiver processor, or the SYSOUT receiver processor assigns a unique JES2 job identifier to a job as it first enters a system in the network. This job identifier number is unique within a JES2 system; while the job remains in a system, JES2 will not assign the same number to another job. In the NJE environment, the NJE job header contains the original job identifier assigned by the input service processor at the entry node. Note that the same job could receive a different job identifier in each system through which it travels. The job header maintains this identifier while the job is in the NJE network.

You can specify a range of numbers (up to 65534) that JES2 assigns to jobs originating at the local node. Use the RANGE= parameter on the JOBDEF statement to specify this range. Installations participating in the JES2 network can coordinate the specification of these parameters, so each node uses a different range of numbers for job identification. Thus, jobs read in at one node and sent to another for execution would always retain the original job identifiers. This is easy to accomplish and useful in a small network.

### **Determining the Destination of Output**

JES2 queues output produced by a job, started task (STC), or TSO/E user either for processing on this node or transmission to another node. JES2 treats a transmission entering the network through the TSO Extensions interactive data transmission facility as an output data set. JES2 uses the TSO/E userid of the intended receiver as the destination userid. JES2 determines the destination node for output in the following ways:

- The originating node is the destination node if you have not explicitly specified a destination.
- The PRTDEST= and PUNDEST= parameters of the RDR(nn) and R(nnnn).RD(m) initialization statements explicitly define the destination.
- A JES2 /\*ROUTE control statement (submitted as part of the job) redefines the destination.
- The DEST= parameter on
  - A JCL OUTPUT statement
  - A JCL DD statement
  - A JES2 /\*OUTPUT control statement

for a specific SYSOUT data set (or groups of data sets) specifies the destination. (DEST=LOCAL specifies that the origin node is the destination node.)

- The DEST= text unit in a dynamic output request by an OUTADD macro specifies the destination. See *z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU* for information about the OUTADD macro.
- JES2 operator commands explicitly define the destination (for example, \$R PRT,J=J5,D=N1R2 or \$T O J5,D=WASH).

JES2 then sends the SYSOUT directly to the destination or the closest intermediate node for store-and-forward transmission.



JES2 queues spin data sets (FREE=CLOSE or SPIN=UNALLOC specified on the DD statement) for transmission as soon as the data set closes, without waiting for the job to end.

JES2 attempts to transmit as one job, any non-spin SYSOUT which are created under a single job and directed to a common destination (or along a common path). This processing is performed even if multiple SYSOUT data sets are grouped into different output groups with different output priorities.

A receiving node processes any output received from other nodes as it would normal output. The system prints the received output when a device that matches that job's characteristics becomes available. (This assumes no other higher-priority work is waiting for the device.) You can also direct data to a particular user. That output will remain on the spool until the intended receiver requests it (or the operator removes it). Use the RECEIVE command to receive "notes" or copy files sent using the TSO/E TRANSMIT command.

---

## Designing the Network

Before you code the initialization statements that define your network, you should design it. Designing your network can minimize the errors resulting from incorrect or incomplete initialization statements for the network. Take the time to draw out the network and determine what physical and logical connections you need to get jobs or output to other nodes. Careful coordination between each remote location is important to avoid problems caused by duplicate node names, incorrect line specifications, unclear resistance values, and other inconsistencies. Make sure that the nodes with which you wish to communicate are accessible to your node either directly, or through other nodes in the network.

## General Considerations

Consider the following topics and questions when designing your network:

### Network Topology

(see "Network Topology" on page 265.)

- What does the network look like?
- How does your node fit into the entire network?
- Do you need alternate paths to particular nodes?
- What connections do you need?
- Is each installation aware of all planned connections?

### Performance

(see "Performance Considerations" on page 268.)

- What should you do to keep work flowing through the network?
- How can you limit the amount of data going through the network?
- What is the best way to get data to a particular node?
- What are the predominant routes in the network, and how can they be optimized to reduce intermediate node store-and-forward activity?

### Security

(see "Security Considerations" on page 269.)

- How do you keep an unauthorized node from signing onto your node, or sending and receiving data both to and from your node?
- How can you protect the data as it travels through the network?

- Is there agreement on the use of nodal passwords?
- When and how will the passwords be changed?
- What kind of protection will the passwords have?
- What command authority should participating nodes have on the individual installations?
- Should that authority be changed by operator commands?

### Node Names

(see “Symbolic Node Names” on page 271.)

- What are the naming restrictions?
- Are there similar names in the network now?
- Which names does JES2 know?
- Do all the installations participating in a SNA NJE network agree on **unique** VTAM application names as specified on the APPL(avvvvvvv) initialization statement?

### Resistance

(See “Determining Path Resistance” on page 301.)

- What is the criteria for assigning resistance values?

The following two considerations are discussed more generally.

**Accounting:** Can the job accounting exit routines process different job accounting fields in use across the network?

**Cost:** Are there any ways to limit the physical resources to reduce the cost of the network?

Each node’s design should be a compromise of all the considerations to best meet your needs.

## Network Topology

Network topology is the physical and logical configuration of host systems and their interconnections. The attachment of host processors, communication controllers and lines, and other mechanisms (such as channel-to-channel adapters or shared DASD) determines the physical configuration of the network.

### Simple Configurations

When designing your network, be aware of the building blocks of networks.

Figure 53 on page 266 illustrates five simple configurations used in constructing networks. The following discusses the configurations presented in Figure 53 on page 266 and some advantages and disadvantages of each.

**Simple 2-Node:** This is the basis of all networks. It provides communication between two nodes but offers no recovery should the link fail.

**2-Node with 2 Parallel Links:** This configuration is the same as the simple 2-node but adds the ability to recover because of an additional line between the two nodes.

**4-Node Ring:** You can use this configuration to join four adjacent nodes. Three nodes can continue to communicate should any one node or link fail. You should be careful implementing this configuration because, if a path definition to any one node is not unique, data could loop through the network if a node fails. For more

information on how to avoid the problems of looping in a network, see “Preventing Looping When Using Connect Statements” on page 297 later in this chapter.




Figure 53. Basic Network Configurations

**4-Node Ring with Full Connectivity:** This configuration allows full communication capability between four nodes. If any one node should fail, the other three nodes will continue to communicate because of the cross communication between nodes 1 and 4, and nodes 2 and 3. This makes the network more reliable and minimizes the queueing of data for the failed node at one particular node.

**5-Node Star:** If most NJE traffic is between a central node and remote nodes, you might wish to use this design. For example, you can place a central data base at node 2, which is also the center of the network. If the central data base becomes unavailable for any reason, node 2 can then shut down the network until the data base becomes available.

## Complex Configurations

As your network grows, so do the problems with managing the network. Cost considerations also begin to grow. It is not practical to have links between every node in a large network, and even logical links between every node might not be a good solution. NJE support for store-and-forward traffic makes it easier to manage growth without adding physical or logical overhead.

When you design a complex NJE network, start with your existing network and use the already-established links to help you build the larger one. Figure 54 on page 267 and Figure 55 on page 268 illustrate two complex configurations.

**Subnets with Gateways:** As networks grow in size and complexity, and as multiple networks interconnect, it is practical to manage networks in pieces with a limited number of control points. For this reason, divide large networks into **subnets** with **gateway** nodes. For a definition of subnets and an example of how gateway nodes can enhance network productivity, see “Defining and Communicating Between Subnets” on page 299. The gateway nodes provide the interconnections

between the subnets, as you can see in Figure 54. These gateways can also provide security, accounting, and control.




Figure 54. Gateway Configuration

**Backbone Network Configuration:** As the number of subnets and interconnections grow, the concept of a **hub** or **backbone** becomes useful in managing the interconnection of NJE traffic. Figure 55 on page 268 shows three subnets "A", "B", and "C" connected through gateway nodes A5, B3, and C3 which comprise the backbone of the network. Using matching CONNECT initialization statements to connect nodes A5 and C3 directly further increases the availability of the backbone. For example, if the lines in Figure 55 on page 268 that connect node A7 to node B1 are down but CONNECT statements have been specified on all nodes, the data collects at gateway node A5, rather than waiting at A-6. When the path becomes active, the data reaches its destination more quickly.




Figure 55. Backbone Network Configuration

## Performance Considerations

Line speeds, processor speeds, length of the path between nodes, and other factors determine how fast your network gets data from one node to another. The amount of data can also delay the data in reaching its final destination. For more information about JES2 initialization parameters that can impact performance greatly, see “Queueing Messages to a Multi-Access Spool Node” on page 311.

JES2 uses **compression** and **compaction** to minimize the amount of data sent through the network.

### Compression

Compression is the method of reducing the size of a file by removing all blanks and duplicate characters which is applicable for all NJE connections. JES2 automatically compresses data sets sent through an NJE network. On a BSC line, you can specify COMPRESS=NO on the LINE(nnnn) initialization statement to turn off compression.

### Compaction

In an SNA environment, you can further reduce the data sent through an NJE network by compacting the data. JES2 uses compaction to represent 8 bits of data in 4 bits. You reduce the data by carefully building a compaction table (using the COMPACT initialization statement) and using that table for the SNA session.

**Note:** Carefully consider the amount of data you are shipping through the network before using compaction. Compaction adds considerable CPU overhead to the session and might not be beneficial when transmitting binary data streams. Compactions is most useful when transmitting text-string data streams. If you are transmitting data to non-JES2 nodes, ensure that they support data compaction.

## Security Considerations

In networking, you must:

- Secure the node, which involves ensuring the proper nodes and users have access to the network
- Secure the data, which involves ensuring that if an unauthorized node or user intercepts the data, that data is not usable by the interceptor.

You should protect your resources at different levels. Security mechanisms include:

- RACF (or an equivalent security product) -- Each node in the network should use RACF to protect its local resources. See “Part 7. Providing Security for JES2” on page 341 for information on implementing security for your network.
- Encryption.
- JES2 passwords.
- JES2 exits.
- Security authorization facility (SAF) exits.
- SMF exits.
- MVS exits and modifications.

In larger networks, implementing security is most commonly done at the points where subnets interconnect, besides the individual node security. Therefore, it is important that the gateway nodes in the network enforce the proper level of security. *NJE Installation* contains a complete discussion of security in large networks.

### Password Processing

JES2 defines passwords associated with NJE lines and with nodes in the NJE network during initialization. Specify line passwords using the `PASSWORD=` parameter of the `LINE(nnnn)` initialization statement for BSC lines. Do not specify a password for SNA lines used for NJE; use the `PASSWORD=` parameter of the `NODE(nnnn)` initialization statement to specify a node password for each node with which another node can communicate in your network. See “Extending Network Capability” on page 306 for additional information.

Installations can encrypt passwords for jobs sent through the network. Use RACF on the submitting node to encrypt a password that is then verified by RACF on the job’s execution node. Before sending jobs with encrypted passwords through the network, ensure that the execution node supports encrypted passwords. Use the `PENCRYPT=` parameter on the `NODE(nnnn)` statement to indicate the nodes that support encryption. See *z/OS JES2 Initialization and Tuning Reference* for a description the `PENCRYPT=` parameter.

### Encryption

You can encrypt a particular line (in which case everything sent on that line is encrypted) or a particular transmission. End-to-end encryption is the process of encrypting a teleprocessing line. You encrypt a teleprocessing line by using cryptographic modems. When using ACF/VTAM, there are software products you can use to encrypt individual sessions. You can also use software products to encrypt specific transmissions before sending them through the network. In this case, the receiver must have the same product and the encryption key to decode the data.

---

## Initializing the Network Job Entry Functions

The following is a guide for the system programmer establishing an NJE network for the first time. This section describes and provides examples for the following tasks:

- “Naming the Nodes in a Network” on page 271
- “Defining a Minimum Configuration for BSC NJE” on page 274
- “Default NJE Parameters (BSC and SNA)” on page 275
- “Using Different Operating Systems in a Network” on page 279
- “Defining a Minimum Configuration for SNA NJE” on page 281
- “Special Considerations for SNA NJE Networking” on page 283
- “Displaying Information About a Network” on page 287

## Initialization Statements

The following initialization statements define a network. (For detailed information about parameter formats, default values, and other coding considerations, see *z/OS JES2 Initialization and Tuning Reference*.)

Table 56. JES2 Initialization Statements that Define a Network

| Statement       | Purpose                                                                                                                                                                                                                                                                                                                                                     |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| APPL(jxxxxxx)   | Associates a JES2 node with a VTAM application identifier and specifies session characteristics for SNA connections.<br><br>An installation does not need this statement if adjacent nodes have the same names (NAME= parameter on the NODE(nnnn) statement) as their VTAM application identifiers.                                                         |
| CONNECT         | Defines a static connection between two nodes.                                                                                                                                                                                                                                                                                                              |
| DESTID(jxxxxxx) | Defines the symbolic name for a JES2 route code, which may define a specific device on a node.                                                                                                                                                                                                                                                              |
| LINE(nnnn)      | Defines the characteristics of a telecommunication line.                                                                                                                                                                                                                                                                                                    |
| LOGON(nnn)      | Specifies the VTAM application identifiers this node uses to communicate with VTAM for an SNA connection. See <i>z/OS Communications Server: SNA Resource Definition Reference</i> for information about defining application identifiers.<br><br>Other nodes that wish to communicate with this node must sign on to one of these application identifiers. |
| MASDEF          | Specifies the characteristics of a multi-access spool configuration.                                                                                                                                                                                                                                                                                        |
| MEMBER(n)       | Specifies the name for each member of a multi-access spool configuration.                                                                                                                                                                                                                                                                                   |
| NETACCT         | Permits network installations to define network account numbers that correlate to local account numbers.                                                                                                                                                                                                                                                    |
| NJEDEF          | Defines the NJE characteristics for this JES2 node.                                                                                                                                                                                                                                                                                                         |
| NODE(nnnn)      | Defines the characteristics of each node in the network.                                                                                                                                                                                                                                                                                                    |
| TPDEF           | Defines the JES2 teleprocessing characteristics: <ul style="list-style-type: none"><li>• Buffer size and placement</li><li>• VTAM sessions</li><li>• Message limits for remote consoles</li></ul>                                                                                                                                                           |



# Naming the Nodes in a Network

The following provides the JES2 initialization parameters to use when naming nodes, routing output, and establishing the sign-on protocol for all nodes communicating throughout a network.

## Default Names

If you do not specify NAME= on the NODE(nnnn) initialization statement or omit the NODE(nnnn) statement, JES2 generates a default symbolic name, in the form Nnnnn, where the nnnn comes from the statement subscript.

## Naming Restrictions

In all communications with other nodes, a node uses its node name (the symbolic name, not the number). These communications include network connection control sign-on records. When verifying a sign-on, the receiving node checks the name received against its list of valid nodes.

**Installations should specify both node names and numbers consistently, or risk having operators receive confusing JES2 operational messages.** Because JES2 messages often display only the node number, an operator could be confused by the situation in Table 57, where N1 is NODEA at one node and NODEB at another.

Table 57. Confusing JES2 Node Naming Conventions To Avoid.

| Node A  |                | Node B  |                |
|---------|----------------|---------|----------------|
| NJEDEF  | OWNNODE=1      | NJEDEF  | OWNNODE=1      |
| NODE(1) | NAME=NODEA,... | NODE(1) | NAME=NODEB,... |
| NODE(2) | NAME=NODEB,... | NODE(2) | NAME=NODEA,... |

JES2 propagates NODE(nnnn) initialization statement names throughout an NJE network, so these names must be unique throughout the network.

## Symbolic Node Names

Use symbolic node names (rather than node numbers) to make individual nodes in your network easier to remember. For example, Honolulu is more memorable to you and your operators than N4358. However, it is not a good idea to use an unqualified city name (for example, DALLAS) because the city name could cause duplicate node name problems when you join two networks together. You should always use some manner of qualification (such as DALLAS1) when naming your nodes. Specify the names you wish to give to each node in the NAME= parameter of the NODE(nnnn) initialization statement. For example, NODE(1) corresponds to POKIPSY1 in the following statement:

NODE(1)     NAME=POKIPSY1

Any following initialization statements or commands can then refer to the name, rather than the number of the node, for example:

This eliminates the need to remember the association between NODE(1) and the  
\$T    NODE(POKIPSY1),AUTH=(JOB=NO)

symbolic name, POKIPSY1. Furthermore, for display purposes (\$D NODE) or for changing NODE characteristics (\$T NODE), you can specify the NODE subscript as a generic form. For example, NODE(POK\*) indicates all nodes with a name beginning with POK.

The symbolic name assigned to a node through the NAME= parameter on the NODE(nnnn) statement should not be of the form NxRx, or Nxxx, which JES2 may incorrectly resolve as a different node.

### Defining Nodes Using Generics

You can minimize the number of statements needed to define your network by using generics to define your nodes. You use generics to define :

1. Common characteristics of **all** nodes
2. Unique characteristics for individual nodes
3. Unique characteristics for groups of nodes.

To clarify this point, study Figure 56 and its explanation immediately following.

```

NODE(*) REST=125
NODE(1) NAME=WASH1,AUTH=(DEVICE=NO,NET=YES)
NODE(2) NAME=WASH2,AUTH=(SYSTEM=NO,JOB=NO)
NODE(3) NAME=WASH3,AUTH=(SYSTEM=NO,NET=YES),HOLD=JOBS
NODE(4) NAME=NYORK1,AUTH=(JOB=NO,NET=YES)
NODE(5) NAME=NYORK2,AUTH=(DEVICE=NO,SYSTEM=NO)
:
NODE(WASH*) REST=250,AUTH=(JOB=NO)
NODE(NYORK*) HOLD=JOBS
```

*Figure 56. Defining Nodes Using Generics*

- The NODE(\*) statement initially assigns a resistance value of 125 as the default for **all** nodes (NODE(1) through NODE(32767)) during initialization statement processing.

When initialization processing completes, JES2 limits the set of affected nodes (1-32767) by the maximum specified in the NODENUM= parameter on the NJEDEF initialization statement.

#### **CAUTION:**

**This may significantly elongate JES2 initialization processing. You should use a more realistic number such as NODE(1-500) rather than NODE(\*).**

- Specific definitions for individual nodes (NODE(1) through NODE(5)) follow to add to or override the previous generic assignment statement.
- The last two statements (NODE(WASH\*) and NODE(NYORK\*)) assign values for groups of nodes.
  - The NODE(WASH\*) statement overrides the values for REST= and AUTH= for all nodes whose names begin with WASH.
  - The NODE(NYORK\*) statement overrides the values for HOLD= for all nodes whose names begin with NYORK.

These values replace those previously defaulted or defined in previous generic statements.

Defining nodes in the network requires careful planning and coordination among participating installations to ensure that JES2 does not encounter duplicate node names. **You** must ensure that a name known to any node is reachable from all nodes.

## Specifying Multiple Passwords for NJE Connections

JES2 allows a node to specify different passwords for each adjacent node. Also, an installation can specify a value for the password it receives from an adjacent node to verify the identity of the node signing on.

To implement these security functions, use the subparameters for the PASSWORD parameter on the NODE(*nnnn*) initialization statement for each directly connected node. Figure 57 shows a JES2 node sending different passwords to different directly-connected nodes. The figure also shows the PASSWORD subparameters that specify the passwords the nodes send and the passwords the nodes expect to receive to establish the connection.




Figure 57. JES2 NJE Sign-On Password Verification

While this security enhancement applies to JES2 Version 4 nodes and nodes for all subsequent releases, you can use the PASSWORD= parameter and its subparameters in a network that contains pre-Version 4 JES2 nodes. An installation does not need to alter the pre-Version 4 initialization statements. Figure 58 shows the password flow for an NJE network with different releases of JES2. Notice that NODE3 is not using the enhanced security feature with NODE2.




Figure 58. NJE Sign-On Password Verification for Mixed Levels of JES2

## Using Destination Identifiers (DESTIDs)

The DESTID(jxxxxxx) initialization statement allows TSO/E users and batch jobs at a given node to refer to symbolic names for local output devices, special local output devices, remote workstations, and userids attached to network nodes.

Specify the symbolic name in the DESTID subscript as either a specific name or a generic name (similar to the NODE(nnnn) subscript).

You can specify any characters on DESTID subscripts except LOCAL and ANYLOCAL if you specify Ndest=USER, RIRMIRMTdest=USER, and Udest=USER on the DESTDEF initialization statement.

If you do not specify USER for the above-mentioned parameters on the DESTDEF initialization statement, IBM recommends that you avoid potential confusion when routing SYSOUT from one destination to another by **not** specifying destids in the form of an explicit JES2 destination (route code):

- Nnnnn
- Rnnnn
- RMnnnn
- RMTnnnn
- Unnnn
- NnnnnRnnnn

Do not code an explicit node number or node name (NAME= value defined on a different NODE(nnnn) statement) for the subscript on a DESTID initialization statement. That is, if you allow the DESTDEF statement parameters to default, you cannot define DESTID(N1) DEST=N2R1, but you can define DESTID(X) DEST=N2R1.

Do not specify a symbolic DEST= parameter which has the same value as a DESTID subscript, unless the DESTID has been previously created in the initialization stream. That is, you cannot define DESTID(TOM) DEST=FRED unless DESTID(FRED) has been previously created in the initialization stream.

The JES2 node that defines the DESTID(jxxxxxxx) name is the only node that knows this subscript name. For an example of how JES2 resolves destination identifiers at both the sending node and the receiving node, refer to “Routing Output to Other Nodes” on page 111, “Using Destination Identifiers to Route Output” on page 143, and “How JES2 Resolves Destinations from Node to Node” on page 147.

## Defining a Minimum Configuration for BSC NJE

During JES2 initialization, you can easily request the NJE feature. The default configuration (shown in Figure 59 on page 275) is a very simple BSC-only network. Include 4 JES2 initialization parameters, NODENUM=, LINENUM=, and OWNNODE= from the NJEDEF statement and the UNIT= parameter from the LINE(nnnn) statement, in your initialization data set. The LINE(nnnn) statement specifies the device address of the line (UNIT=) and enables the text transparency feature (TRANSPAR=).

NODE 1 in Figure 59 on page 275 defines NEWYORK1 as the first node in the network. NODE 2 in the figure does the same for the second node (WASHDC2). The simple network illustrated in Figure 59 on page 275 shows how to use the NJEDEF statement parameters: NODENUM=, LINENUM=, and OWNNODE=. JES2 uses default values for the remaining NJE parameters.




Figure 59. Minimum NJE Configuration (BSC only)

## NODENUM

The value of NODENUM= specifies the maximum number of nodes in the network to which a particular system belongs. The network in Figure 59 has two nodes. If your network is growing, you may wish to specify a value greater than the actual number of nodes. This way, you avoid changing this parameter every time you add new nodes.

## LINENUM

The value of LINENUM= specifies the number of lines JES2 uses for NJE communications. For BSC NJE to use a line, the BSC adapter must have the text transparency feature. Therefore, the LINE(nnnn) statement must specify TRANSPAR=YES this enables the text transparency feature. Specifying LINENUM alone does not dedicate lines to NJE.

## OWNNODE

The value of OWNNODE= specifies the node number assigned to this node. In a multi-access spool configuration, each JES2 member must specify the same value of OWNNODE=, because JES2 considers the entire configuration as one node (see “Defining a Multi-Access Spool Node (SNA Considerations)” on page 312). Installations should coordinate the specifying of OWNNODE= values to ensure that each node has a unique symbolic name.

## Default NJE Parameters (BSC and SNA)

Referring again to Figure 59, including the NJEDEF parameters LINENUM=, NODENUM=, and OWNNODE= in the JES2 initialization streams of these two systems created an NJE network. Because only these NJE options appear on the statements, JES2 uses default options for the remaining NJE parameters. These options provide the capability to send and receive data, detect lockout situations, route output, specify the difference between TOD clocks at each node, and provide command authority.

## Sending and Receiving Jobs and SYSOUT

All networks have the following capabilities; each node can:

- Send one job and one SYSOUT data set to the other node simultaneously.
- Receive a single job and SYSOUT data set from the other node simultaneously.

To send and receive multiple jobs and SYSOUT data sets (up to 8 in a single transmission) concurrently, override the default values for the JTNUM=, JRNUM=, STNUM=, and SRNUM= parameters on the NJEDEF initialization statement described in “Specifying Transmitters and Receivers”. To control the flow of jobs and SYSOUT data sets in a network, see “Specifying Work Selection Values for NJE Transmitters” on page 277.

**Specifying Transmitters and Receivers:** An installation can specify a maximum of 16 devices (8 transmitters and 8 receivers) on a line. Each transmission, however, can consist of no more than 8 data sets (limited to a maximum of 7 jobs and 7 SYSOUT). The number of transmitters active on a line must match the number of receivers on the other end of the line; JES2 will drain excessive (unmatched) transmitters and receivers.

You can specify the number of transmitters and receivers on NJE lines globally through the following NJEDEF parameters, which apply to each line generated by the NJEDEF LINENUM parameter:

- JRNUM - Number of Job Receivers for each NJE line
- JTNUM - Number of Job Transmitters for each NJE line
- SRNUM - Number of SYSOUT Receivers for each NJE line
- STNUM - Number of SYSOUT Transmitters for each NJE line.

You can specify the value DEFAULT on these parameters to take the value specified on the NJEDEF statement. However, if the use of DEFAULT would result in more than eight transmitters (job and SYSOUT combined) or more than eight receivers (job and SYSOUT combined), JES2 reduces the defaulted value so that the combined number of transmitters and receivers equals 8.

Installations can commit lines to NJE through either the JRNUM=, JTNUM=, SRNUM=, and STNUM= parameters on the LINE(nnnn) statement or through the L(nnnn).ST(m) or L(nnnn).JT(m) statements. (These lines do not count toward the limit specified on the LINENUM= parameter of the NJEDEF initialization statement.) In addition to committing these lines to specific devices, IBM recommends that each installation dedicate all lines for an NJE facility. To dedicate these lines, specify them on the LINE= parameter on either the APPL(avvvvvvv) initialization statement (for SNA and BSC networks) or the NODE(nnnn) initialization statement (for BSC networks only). If you specify different values for the LINE= parameter on both statements, JES2 uses the value on the APPL(avvvvvvv) statement.

NJE transmitters can also be specified explicitly through the following statements:

- L(nnnn).JT(m) - Job transmitters for line nnnn - parameters WS=(LIMIT= can be used for selection criteria.
- L(nnnn).ST(m) - SYSOUT transmitters for line nnnn - parameters WS=, LIMIT=, and PLIM= can be used for selection criteria.

If this statement is specified for a line, then a full set of transmitters and receivers will be assigned according to the NJEDEF or LINE xxNUM parameters, where xx indicates SYSOUT transmitter (ST), SYSOUT receiver (SR), job transmitter (JT), or

job receiver (JR). If the number (m) is higher than the number specified by the corresponding JTNUM or STNUM parameter, the specific transmitter specified through (m) is not created.

**Specifying Work Selection Values for NJE Transmitters:** You can use the work selection (WS=) parameter on the L(nnnn).JT(m) or L(nnnn).ST(m) statement to cause an NJE transmitter to select files based on their size. This allows you to optimize NJE transmissions. For example, by dedicating some transmitters to large files and others to small files, you can ensure that small files are not always forced to wait for completion of large file transmissions. You can set the limits based on the size in cards, lines or pages, depending on whether the file is cards, or page-mode or line-mode data sets. If you specify both page mode and line mode, a job must fit within both limits before JES2 will select it. For example, if you specify

```
L21.ST1 WS=(LIM/),LIMIT=0-5,PLIM=0-5
```

JES2 selects the job only if the output consists of a minimum of 0 to a maximum of 5 pages and lines.

The following example shows how to set up two transmitters, the first one for large files, and the second for small files:

```
L23.ST1 WS=(LIM/),LIMIT=0-*,PLIM=0-* /* all files can use */
L23.ST2 WS=(LIM/),LIMIT=0-100,PLIM=0-5 /* reserved for small */
```

**Considerations When Specifying NJE Transmitters and Receivers:** Because there are several ways to specify NJE transmitters and receivers, you must coordinate these statements and parameters to maintain normal NJE functions:

- If you do not want to use work selection characteristics, and you want the same number of transmitters or receivers on each NJE line, then use the NJEDEF parameters.
- If you do not want to use work selection characteristics, but you want to specify different numbers of transmitters or receivers on each NJE line, then use the parameters on the LINE statement.
- If you want to specify work selection characteristics for a Job transmitter, then use the L(nnnn).JT(m) statement.
- If you want to specify work selection characteristics for a SYSOUT transmitter, then use the L(nnnn).ST(m) statement.
- If you use the L(nnnn).JT(m) or L(nnnn).ST(m) statement, ensure that you have specified all possible ranges of both line and page sizes for your installation. If you do not, you could leave some jobs without transmitters. To avoid such omissions, you can define one transmitter with an infinite size range and then define others with descending size ranges, for example:

```
L23.ST1 WS=(LIM/),LIMIT=0-*,PLIM=0-*
L23.ST2 WS=(LIM/),LIMIT=0-100,PLIM=0-2
L23.ST3 WS=(LIM/),LIMIT=0-1000,PLIM=0-20
L23.ST4 WS=(LIM/),LIMIT=0-10000,PLIM=0-200
```

This ensures that there will always be one transmitter capable of transmitting any size SYSOUT data sets over the line.

- On L(nnnn).JT(m) or L(nnnn).ST(m) statements, use asterisks (\*) only to represent any pre-defined lines or transmitters. Asterisks do not create transmitter definitions; they only change existing definitions.

For example, assume that lines 2, 3, and 4 have already been defined by the following LINE statements:



```

LINE 2 TRANSPAR=YES,UNIT=00E
LINE 3 TRANSPAR=YES,UNIT=338
LINE 4 TRANSPAR=YES,UNIT=261

```

To define SYSOUT transmitters for these lines, you must code an explicit line number and transmitter number (or range of numbers) on the L(nnnn).ST(m) statement, for example:

```

L(2).ST(1) WS=...
L(3).ST(1-3) WS=...
L(3-4).ST(4-7) WS=...

```

After the transmitters are explicitly defined, you can use asterisks to change the definitions, for example:

```

L(2).ST(*) WS=... (changes all SYSOUT transmitters on Line 2)
L(3).ST(*-3) WS=... (changes SYSOUT transmitters 1-3 on Line 3)
L(3-*).ST(3-*) WS=... (changes SYSOUT transmitters 3-7 on Lines 3-4)

```

- Be careful not to define transmitters for lines meant for RJE use. RJE cannot be done on lines with transmitters or receivers assigned. Use the \$DU command to determine if a line has transmitters or receivers assigned:

```
$DU,LINES
```

## Controlling Jobs Looping in the Network

You can control the number of intermediate nodes through which a job (or SYSOUT) will be routed before JES2 determines that the data is looping in the network. The MAXHOP= parameter on the NJEDEF statement specifies the maximum number of nodes (0-65535) through which a job can travel before it is placed in hold. This parameter applies only to jobs arriving at this node from another node, not to jobs submitted locally.

JES2 begins the node count when the job is submitted and continues incrementing the count until the job prints. An installation can reset the count through both the \$R command and the \$T O command. To understand how to reset the count and alter the characteristics of output routed across a network, see *z/OS JES2 Commands*.

Specify a MAXHOP= value greater than twice the number of nodes in the longest path in your network. This allows for a job to traverse the network and output to return, plus an additional allowance if necessary for alternate path routing. If you do not specify a value for MAXHOP=, it defaults to 0. This parameter does not count traffic travelling through intermediate nodes in the network.

## Routing Output

Node 1's PRT1 (in Figure 59 on page 275) processes all normal print output produced by jobs that entered the network at node 1's RDR1. For jobs entering the network at node 2's RDR1, node 2's PRT1 will receive all normal print output. To alter the default routing of output to some other node in the network, use either the PRTDEST= or the PUNDEST= parameter on the RDR(nn) initialization statement. You can modify both parameters by using the \$T RDR1 operator command.

## Command Authority

In Figure 59 on page 275, each node in the figure has sufficient command authority to affect jobs that it owns at the other node. Use the AUTH= parameter on the NODE(nnnn) statement to limit or expand this command authority. To understand how individual systems maintain security, see "Part 7. Providing Security for JES2" on page 341 and *z/OS SecureWay Security Server RACF Security Administrator's Guide*.

## Network Time Tolerance

The TIMEtol= parameter specifies in minutes, the number of minutes difference (0-1500) that JES2 allows between different time-of-day (TOD) clocks located at adjacent nodes at sign-on. Because the NJEDEF statements in Figure 59 on page 275 do not specify TIMEtol=, JES2 uses the default value of 1440 minutes (24 hours). If the difference between the time on the TOD clocks at each of the nodes is greater than 1440 minutes, the network rejects attempts by this node to start a session.

IBM recommends that you use GMT time and correct time zone offset for your system's TOD clock setting.

## Using Different Operating Systems in a Network

You should consider the following features of JES2 processing when running in a network composed of operating systems other than z/OS JES2 (VSE/POWER, RSCS/VM, AS/400, z/OS JES3). In particular, there are processing considerations for execution nodes and job output nodes.

### Execution Node Considerations

**User Access Authority (RACF):** If your installation uses RACF or any other access control facility to secure data, the user identified on the JOB statement or in the job header must be defined at the execution node with the proper password supplied.

**Job Account Numbers:** If your installation uses the JES2 4-character account numbers, you can use translation services to map from one set of local account numbers to another. Use either the NETACCT initialization statement or the /\* NETACCT JECL statement to make an account number available to all nodes in a network. Installations can use the network job header to transmit and receive an accounting section that is composed of the complete accounting string used on the JCL JOB statement to create the job.

When specifying multiple NETACCT initialization statements to determine how network account numbers are converted to JES2 (local) account numbers, ensure that any ranges specified do not overlap. If they do, the second NETACCT statement overlays the first; JES2 does not convert network account numbers that were only specified in the first NETACCT statement into local (JES2) account numbers.

In the following example, the second NETACCT initialization statement specifies a range (A33 to B0) that overrides the range (A11 to B0) specified by the first statement. All jobs received from the network with network account number from A11 to A32 would not receive a JES2 (local) account number.

```
NETACCT NACCT=A11,NTHRU=B0,JACCT=AAA,TYPE=BOTH
NETACCT NACCT=A33,NTHRU=B0,JACCT=3AA,TYPE=BOTH
```

A local job specified 'AAA' would still be sent into the network account number in the range A11 to B0.

**Job Accounting Information:** The system management facility (SMF) gathers and records information that installations can use to evaluate system usage. Specifically, the SMF Type 26 record records system identifiers that indicate which system in the configuration performed each major function of processing for a job such as input, conversion, execution, post-execution, breaking into output elements,

and purging. Although job accounting information is completely written to type 5 and type 35 records, those records are not created unless the job runs.

JES2 records the entire contents (up to 142 bytes) of the JOB accounting field into the accounting section of the network job header. This header is transmitted to other nodes with jobs and SYSOUT. The accounting information for a job is available to all nodes in the SMF Type 26 record.

**Procedure Libraries:** JES2 converts and interprets all jobs on the execution node. You may need to copy commonly used procedures to other nodes for use by a larger set of installations.

**Unit Names:** You should standardize unit names across the network to avoid confusion when transmitting jobs to execute on remote nodes. For example, specifying UNIT=3400-16 on the JCL DD statement for all devices in the network avoids confusion.

## Output Node Considerations

**Held Output:** JES2 transmits data sets held for Time Sharing Option Extensions (TSO/E) retrieval to their destination node and then places the data sets in the hold queue. (See “Defining Held Data Sets” on page 157 for more information about held data sets.)

The TSO/E OUTPUT command allows a user to view, print, or copy held output if the job name is the same as the receiving TSO/E userid plus one or more characters. On JES2 Version 3.1.3 and above, installations can replace the job name restriction by specifying RACF check of the JESSPOOL class. For more information on how to replace this restriction, see *z/OS TSO/E Customization*.

**Lines Per Page:** If your output must have a specific number of lines per page, you must use the LINECT parameter in your JCL. The default used for this parameter when processing the output is the value of the LINECT= parameter on the PRINTDEF initialization statement of the printing subsystem.

**FORMDEF and PAGEDEF:** JES2 permits both FORMDEF and PAGEDEF names to be associated with any SYSOUT data set. Use the OUTPUT JCL statement specify form characteristics (FORMDEF) or to format the data itself (PAGEDEF). For more information on specifying either parameter, see *z/OS MVS JCL User's Guide*.

**JESNEWS:** The JESNEWS data set, used to share news among all processors in a multi-access spool configuration, is sent to other nodes with the JESMSGGLG data set. The JES2 print processor only prints this data set on local or RJE printers attached to the node at which the JESNEWS data set is defined. To create a JESNEWS data set, see “Creating a JESNEWS Data Set” on page 137.

**SYSOUT Classes:** SYSOUT classes should be carefully coordinated throughout a network. All characteristics specified on the transmitting system are in effect on the system to which JES2 routes the output. Ensure that the following forms of SYSOUT are known to all nodes in the network:

- Dummy classes
- Held classes
- Print classes
- Punch classes
- OUTDisp= specifications

## Defining a Minimum Configuration for SNA NJE

Figure 60 on page 282 shows 5 different ways of configuring SNA sessions. These are:

1. Over one or more synchronous data link control (SDLC) lines through a pair of communication controllers. A single transmission group defines any set of multiple lines.
2. Over multiple SDLC lines through intermediate communication controllers. A single transmission group defines these lines.
3. Through a single communication controller channel attached to two systems.
4. Through a CTC adapter controlled by ACF/VTAM
5. Through VTAM between two copies of JES2 in the same processor.

When 2 copies of JES2 in the same processor are communicating through VTAM (intra-domain NJE session), there is no need for a communication controller or lines to establish the link. Testing new versions of networking software is the most common reason for using this configuration.




Figure 60. Basic SNA Configurations

A minimum SNA configuration is similar to the minimum BSC configuration depicted in Figure 59 on page 275. Notice that the SNA configuration (Figure 61 on page 283) also requires the four JES2 initialization parameters required in the minimum BSC configuration (NODENUM=, LINENUM=, and OWNNODE= on NJEDEF and the UNIT= on the LINE(nnnn) initialization statement). The capabilities of an SNA network are the same as those previously discussed for a BSC network. When using an SNA session to connect the nodes, supply a LINE(nnnn) initialization statement specifying the UNIT=SNA parameter in the initialization data set. You also need the LOGON(1) statement shown in Figure 61 on page 283 to

specify the application name VTAM uses for this node. (In this case, it is set to the node name.)




Figure 61. Minimum NJE Configuration (SNA)

## Special Considerations for SNA NJE Networking

Controlling SNA NJE networking is similar to controlling binary synchronous communication (BSC) networking. However, because VTAM controls SNA NJE application-to-application sessions, you must meet certain VTAM requirements before establishing a session between two JES2 nodes. See *z/OS Communications Server: SNA Resource Definition Reference* for descriptions of the VTAM definitions needed. To establish a session:

1. You must start VTAM before you establish a session between 2 nodes. VTAM must have the application names defined for the starting node and for all nodes eligible for application-to-application sessions with other nodes in the network.
2. The VTAM network must complete its initialization. This includes activating the IBM 3704, 3705, 3720, 3725, or 3745 Network Control Programs, synchronous data link control (SDLC) links, and all participating VTAM cross-domain resource managers.
3. LOGON(nnn) initialization statements must uniquely define each JES2 subsystem to VTAM.

In the networking environment, each JES must have a unique application name. JES2 uses a default name if APPLID= is not specified on the LOGON(nnn) statement. You should always code the APPLID= parameter on the LOGON(nnn) statement because only one subsystem in the network can use the default name of JES2.

The APPL(avvvvvvv) initialization statement defines the VTAM application name for each node with which an installation plans to connect. In addition, the APPL(avvvvvvv) statement specifies the specific characteristics of an application session. If an application name matches the NAME= parameter on the NODE(nnnn) statement, JES2 can create an APPL(avvvvvvv) statement dynamically during sign on through a \$S N command.

Installations should ensure that the APPL(avvvvvvv) initialization statement is properly specified before attempting to initiate sign on with another node. If the APPL(avvvvvvv) provides an incorrect node name (NODE=), line (LINE=) or compaction table (COMPACT=), installations can often establish a VTAM session, but are unable to activate the NJE session.

4. LINE(nnnn) JES2 initialization statements must define (with the UNIT=SNA parameter) the paths for each NJE session.
5. NODE(nnnn) initialization statements define all NJE applications participating in the network.
6. The operator must issue a \$\$ LOGON(nnn) (start logon) command to connect the NJE application with VTAM.

Once you meet the VTAM session requirements, you can start a session with another eligible JES2 NJE application by issuing the \$\$ N command with the appropriate application or node name specified.

### Multiple Parallel SNA NJE Sessions Between Two Nodes

SNA NJE protocols in JES2 prohibit multiple SNA sessions between two VTAM APPLIDs. However, using multiple APPLIDs per node, each with a unique logon identifier, you can start multiple SNA NJE sessions between two adjacent nodes. You can define up to 999 unique APPLIDs and logon identifiers for each node. In the example below, each node has three unique LOGON(n)s and three APPLID statements which can be started in parallel on three different SNA lines.




Figure 62. Parallel SNA NJE Sessions Between Two Nodes



## VTAM Definitions for SNA NJE

JES2 uses ACF/VTAM services to communicate with other NJE nodes through SNA sessions. The APPL and MODETAB members deserve special mention for NJE and are discussed below.

### VTAM APPL Statement

The NJE application (the JES2 subsystem) requires a few values from the VTAM APPL statement:

Table 58. VTAM APPL Statement Parameters Necessary for a JES2 Connection

| Parameter | Purpose                                                                                                                                                                                                                                                                                                                                                                            |
|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| AUTH=ACQ  | Allows the NJE member to acquire the LU session.                                                                                                                                                                                                                                                                                                                                   |
| NAME=     | Points to the logmode table entry.                                                                                                                                                                                                                                                                                                                                                 |
| VPACING=  | Prevents one node from overrunning another with SNA buffers by controlling the rate of transmission at both the primary and the secondary LU.<br><b>Note:</b> For the primary LU (the node that issued the \$SN command), you must also use a non-zero SSNDPAC value from the secondary LU's logmode table entry. The SSNDPAC value provides the primary LU's inbound pacing rate. |

### NJE Bind Image

JES2 uses a standard bind image for communication with other NJE nodes. The bind image shown below illustrates the standard NJE session parameters. It is not necessary to specify or to include most of these parameters in the input bind image, but all are shown here for completeness.

```
MODEENT LOGMODE=(name),TYPE=X'01',FMPROF=X'03',TSPROF=X'03', C
PRIPROT=X'72',SECPROT=X'72',COMPROT=X'4020', C
SSNDPAC=X'03',SRCVPAC=X'03',RUSIZES=X'0000', C
PSNDPAC=X'03',PSERVIC=X'0000000000000000000000000000'
```

#### TYPE=X'01'

Specifies the type of bind image. In this case, X'01' indicates a non-negotiable bind. JES2 provides this default value.

#### FMPROF=X'03'

Specifies the function management profile. JES2 provides this default value.

#### TSPROF=X'03'

Specifies the TS (transmission services) profile. JES2 provides this default value.

#### PRIPROT=X'72'

Specifies the FM primary LU protocols. JES2 provides this default value.

#### SECPROT=X'72'

FM Secondary LU protocols. JES2 provides this default value.

#### COMPROT=X'4020'

Specifies the common LU protocols. JES2 provides this default value.

#### SSNDPAC=X'03'

Specifies the secondary LU send pacing count. Set this to a non-zero value to allow VPACING from the APPL to be used for the secondary LU to primary LU pacing count.

**SRCVPAC=X'03'**

Specifies the secondary LU receive pacing count. This parameter is not used for APPL-to-APPL sessions.

**RUSIZES=X'0000'**

Specifies the maximum RU (response or request unit) size for both inbound and outbound buffers.

The LOGMODE table entry value is not used. Instead, JES2 uses the value from the TPDEF SNABUF=SIZE= parameter, after rounding down to a valid RU size (if necessary). For a table of acceptable RU sizes, refer to Figure 63.

**PSNDPAC=X'03'**

Specifies the primary LU send pacing count. This value is used for the Primary LU to secondary LU pacing.

**PSERVIC=X'00000000000000000000000000000000'**

Specifies the LU Presentation Services Profile. Because no profiles are specified for NJE, you should leave the value at zeros or omit this parameter.

**SNA Buffer Size**

Each teleprocessing buffer for SNA is prefixed in storage with an RPL. The size of buffers for SNA RJE and SNA NJE is determined by the following:

1. Start with the SIZE= subparameter (within a range of 256-32512) on the SNABUF parameter of the TPDEF initialization statement.
2. If the SIZE= subparameter is less than any BUFSIZE= parameter value on a SNA RMT(nnnn) initialization statement, SIZE= is increased to the BUFSIZE value.
3. If this number is less than 280 and the LINENUM= parameter on the NJEDEF initialization statement is greater than zero, SIZE=280.
4. The size of the RPL prefix (256) is added to the buffer size, rounded up to a multiple of 8, and rounded down to a maximum of 4096.
5. The 'usable' teleprocessing (TP) buffer size is calculated by subtracting the RPL prefix area. This value can be displayed through a \$D TPDEF operator command, which results in the \$HASP839 message display.

**Valid RU Sizes:** The actual transmission RU size for SNA NJE buffer can be further limited (rounded down) by the SNA Architecture which only allows RU sizes that can be described by the formula

$$M * 2^{**}E$$

where M (mantissa) and E (exponent) are integers between 1 and 15.

For NJE connections, the actual transmission data buffer size used is equal to the smaller buffer size of the two adjacent nodes. This is negotiated independently for each NJE session through the functional management header (FMH-4) records. Some NJE systems require that a valid RU size be used in the negotiation. Therefore, you should pick a buffer size from Figure 63.

|     |     |      |      |      |      |      |      |      |      |     |       |
|-----|-----|------|------|------|------|------|------|------|------|-----|-------|
| 512 | 768 | 1024 | 1280 | 1536 | 1792 | 2048 | 2560 | 3072 | 3584 | ... | 30720 |
| 640 | 896 | 1152 | 1408 | 1664 | 1920 | 2304 | 2816 | 3328 | 3840 | ... | 32512 |

Figure 63. Valid SNA Request Unit Sizes (Between 512 and 32512)

## Specifying Unique Log Mode Table Entries for Specific SNA Connections

JES2 allows an installation to specify a different VTAM log mode table entry for each node. The installation specifies the entry to use on the LOGMODE= parameter on the NODE(*nnnn*) or APPL(*xxxxx*) initialization statement. If both statements appear, VTAM uses the entry specified on the APPL(*xxxxx*) initialization statement for the node to locate the corresponding log mode entry. Figure 64 shows the relationship between the APPL(*xxxxx*) statement and the log mode entries.




Figure 64. Using Multiple SNA Log Mode Table Entries

If you determine that specifying different log modes for adjacent nodes can improve your network performance, specify the value for the log mode table entry for the adjacent nodes on the LOGMODE= parameter on either the NODE(*nnnn*) or APPL(*xxxxx*) initialization statement.

If you do not specify the LOGMODE= parameter on a JES2 initialization statement, the default logmode table entry name is specified on the DLOGMOD= parameter of the VTAM APPL statement at each node.

---

## Displaying Information About a Network

You can use the following commands to display attributes of both the local node and remote nodes throughout the network. A brief overview of the console display created by each command follows. For more information on using each command, see *z/OS JES2 Commands*.

### **\$D NJEDEF**

Display NJE global parameters

### **\$D NODE**

Display node attributes

### **\$D APPL**

Display JES2 applications for JES2 NJE

### **\$D DESTID**

Display symbolic destination identifiers

### **\$D PATH**

Display active paths in a network

### **\$D CONNECT**

Display NJE connections

**\$N,D=node,'\$D xxx'**

Send a display command to another (JES2) node

## Displaying NJE Global Parameters

Specify the display NJEDEF (\$D NJEDEF) command to display the global parameters that apply to all NJE sessions.

**\$d njedef**

```
$HASP831 OWNNAME=POK,OWNNODE=1,DELAY=120,
$HASP831 HDRBUF=(LIMIT=10,WARN=80,FREE=10),JRNUM=1,
$HASP831 JTNUM=3,SRNUM=4,STNUM=3,LINENUM=3,MAILMSG=NO,
$HASP831 MAXHOP=0,NODENUM=5,PATH=1,RESTMAX=79992000,
$HASP831 RESTNODE=100,RESTTOL=0,TIMETOL=1440
```

## Displaying Node Attributes

Specify the display node (\$D NODE) command without any parameters to display all the attributes specified on a NODE(nnnn) initialization statement (and operator command settings), as well as its status (such as what line can be used to reach that node).

**\$d node(wscvm)**

```
$HASP826 NODE(2) 844
$HASP826 NODE(2) NAME=WSCVM,STATUS=(VIA/LINE36),AUTH=(
$HASP826 DEVICE=NO,JOB=YES,NET=NO,SYSTEM=NO),
$HASP826 TRANSMIT=BOTH,RECEIVE=BOTH,HOLD=NONE,
$HASP826 PENCRYPT=NO,ENDNODE=NO,REST=0,SENTREST=ACCEPT
$HASP826 COMPACT=0,LINE=0,LOGMODE=,PASSWORD=(
$HASP826 VERIFY=(NOTSET),SEND=(NOTSET)),
$HASP826 PATHMGR=NO,PRIVATE=NO,SUBNET=VNET,TRACE=NO
```

When you use filtering, the display is more tabular:

**\$d node(pok\*),name,status**

```
$HASP826 NODE(3172) NAME=POK,STATUS=(VIA/LINE36)
$HASP826 NODE(3178) NAME=POKCAD1,STATUS=(VIA/LINE36)
$HASP826 NODE(3182) NAME=POKMCR,STATUS=(VIA/LINE36)
$HASP826 NODE(3184) NAME=POKMVSP,STATUS=(VIA/LINE36)
$HASP826 NODE(3188) NAME=POKVMCR3,STATUS=(VIA/LINE36)
:
```

## Displaying JES2 Applications for SNA NJE

Use the display SNA NJE applications (\$D APPL) command to display applications known to JES2 (through the APPLID initialization statement):

**\$D APPL(\*),NODE=1**

```
$HASP821 APPL(WZ1JNJE) NODE=1,COMPACT=0,LINE=0,LOGMODE=,REST=0
```

## Display Symbolic Destination Identifiers

Specify the display destid (\$D DESTID) command to display the symbolic destination identifiers that have been defined at a particular node.

**\$d destid(\*)**

```
$HASP822 DESTID(POK) DEST=N1,STATUS=NODENAME+DESTID,
$HASP822 DESTID(REMOTE20) DEST=R20,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE21) DEST=R21,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE22) DEST=R22,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE23) DEST=R23,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE24) DEST=R24,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE25) DEST=R25,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE26) DEST=R26,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE27) DEST=R27,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(REMOTE34) DEST=R34,STATUS=DESTID,PRIMARY=NO
```

```

$HASP822 DESTID(REMOTE5) DEST=R5,STATUS=DESTID,PRIMARY=NO
$HASP822 DESTID(SANJOSE) 052
$HASP822 DESTID(SANJOSE) DEST=N3,STATUS=NODENAME+DESTID,
$HASP822 PRIMARY=NO
$HASP822 DESTID(WSC) 053
$HASP822 DESTID(WSC) DEST=N2,STATUS=NODENAME+DESTID,
$HASP822 PRIMARY=NO

```

## Displaying Active Paths in a Network

Use the display path (\$D PATH) command to display all active paths to the node (or list of nodes), the total resistance of each path, and the status of each path. You can use this command first to determine if there is a connection to another path and what path(s) or route(s) exist. Note that a comma between nodes indicates a direct path, while an ellipsis (...) indicates that nodes must travel through a subnet to transmit and receive data.

### \$d path(\*)

```

$HASP231 PATH(SANJOSE) STATUS=(THROUGH LINE11),REST=120,
$HASP231 PATH=(POK,FISHKILL,BEACON,NEWBURGH,
$HASP231 CHICAGO,SANFRAN...SANJOSE)
$HASP231 STATUS=(THROUGH LINE20),REST=150,
$HASP231 PATH=(POK,NYC,SANDIEGO...SANJOSE)

$HASP231 PATH(SANDIEGO) STATUS=(THROUGH LINE11),REST=120,
$HASP231 PATH=(POK,FISHKILL,BEACON,NEWBURGH,
$HASP231 CHICAGO,SANFRAN...SANDIEGO)
$HASP231 STATUS=(THROUGH LINE20),REST=150,
$HASP231 PATH=(POK,NYC,SANDIEGO)

$HASP231 PATH(MOSCOW) STATUS=(THROUGH LINE20),REST=300,
$HASP231 PATH=(POK,NYC,LONDON,PARIS,ROME...VENICE,
$HASP231 BRUSSELS,BONN...BERLIN,GLASGOW,LENINGRD
$HASP231 ...MOSCOW)

$HASP231 PATH(BAGHDAD) STATUS=(UNCONNECTED)

```

## Displaying NJE Connections

Use the display connection (\$D CONNECT) command to display the connection between a pair of nodes or all of the connections from a given node. You can also use the \$D CONNECT command to display the type of connection; the time and date the connection was made; and when this node received the information.

### \$d connect,na=wsc

```

$HASP815 CONNECT NODEA=WSC,MEMBERA=1,NODEB=POK,
$HASP815 MEMBERB=1,REST=100,STATUS=ACTIVE,STATE=ACTIVE
$HASP815 STATIC=NO,PATHMGR=YES,CES=(92/045,12:45:23),
$HASP815 TIME=(92/045,13:20:18)

$HASP815 CONNECT NODEA=WSC,MEMBERA=1,NODEB=SANJOSE,
$HASP815 MEMBERB=1,REST=100,STATUS=ACTIVE,STATE=ACTIVE
$HASP815 STATIC=NO,PATHMGR=YES,CES=(92/045,12:42:12),
$HASP815 TIME=(92/045,13:20:19)

$HASP815 CONNECT NODEA=ENDICOTT,MEMBERA=1,NODEB=WSC,
$HASP815 MEMBERB=1,REST=8000,STATUS=ACTIVE,STATE=PENDING
$HASP815 STATIC=YES,PATHMGR=YES,TIME=(92/045,12:05:10)

```

The \$HASP815 message displays node WSC's connections to nodes POK, SANJOSE, and ENDICOTT. The NA= and NB= display parameters are interchangeable: JES2 displays 'WSC' on the third connection, even though it is the

node B connected to ENDICOTT, not the Node A specified on the command. Only the connection between ENDICOTT and WSC is a static connection made through a CONNECT initialization statement.

JES2 displays the time when NodeA and NodeB established a connection through the CES= parameter, and displays when this node last obtained new status information about the connection.

## Sending a Display Command

Use the \$N command to send a command to another node and get a display of the NJE parameters that apply to all nodes on a network. For example, the NJEDEF and NODE definitions on adjacent nodes:

```
$N,D=adjacent_nodename,'$D NJEDEF'
$N,D=adjacent_nodename,'$DNODE(our_nodename)'
```

```
$N,D=WSCMVS,'$D NJEDEF'
```

```
N4 M1 $HASP831 NJEDEF OWNNAME=POK,OWNNODE=1,DELAY=120,
N4 M1 $HASP831 HDRBUF=(LIMIT=10,WARN=80,FREE=10),JRNUM=1,
N4 M1 $HASP831 JTNUM=3,SRNUM=4,STNUM=3,LINENUM=3,MAILMSG=NO,
N4 M1 $HASP831 MAXHOP=0,NODENUM=5,PATH=1,RESTMAX=79992000,
N4 M1 $HASP831 RESTNODE=100,RESTTOL=0,TIMETOL=1440
```

```
$N,D=WSCMVS,'$DNODE(MVSJES2)'
```

```
N4 M1 $HASP826 NODE(9) NAME=MVSJES2,STATUS=(VIA/LINE5),AUTH=(
N4 M1 $HASP826 DEVICE=NO,JOB=YES,NET=NO,SYSTEM=NO),
N4 M1 $HASP826 TRANSMIT=BOTH,RECEIVE=BOTH,HOLD=NONE,
N4 M1 $HASP826 PENCRIPT=NO,ENDNODE=NO,REST=0,
N4 M1 $HASP826 SENTREST=ACCEPT,COMPACT=0,LINE=0,
N4 M1 $HASP826 LOGMODE=,PASSWORD=(VERIFY=(SET),SEND=(SET)),
N4 M1 $HASP826 PATHMGR=YES,PRIVATE=YES,SUBNET=,TRACE=NO
```

This command can also help you determine if the node is at JES2 Version 4, JES2 Version 5, or on an earlier version. For example:

- Only JES2 Version 4.1 and above have PATHMGR= on the NODE parameters.
- Only JES2 Version 4.2 and above have MAXHOP= on the NJEDEF statement.
- Only JES2 Version 4.3 and above have MAILMSG= on the NJEDEF statement.
- Only JES2 Version 5.1 has HDRBUF= on the NJEDEF statement.

---

## Connecting the Network

After the nodes are defined, each node must be connected to form a network. You connect a node to the network using initialization statements and operator commands.

There are two ways to connect nodes to a network:

- Dynamic connections (see “Starting BSC Dynamic Connections” on page 291 and “Starting SNA Dynamic Connections” on page 291)
- Static connections (see “Static Connections” on page 295)

Dynamic connections are created when JES2 nodes sign on to one another through the \$S N command, while static connections are defined during initialization through the CONNECT statement and dynamically by operators through the \$ADD CONNECT command.

JES2 also keeps an internal representation of the network, which is controlled by a feature called the path manager.

## Starting BSC Dynamic Connections

At connection time, operators at both nodes involved in the connection must issue the start line command. A `$$ LINE(nnnn)` command instructs JES2 to prepare a line for transmission. For a bisynchronous (BSC) NJE connection, the `UNIT=` parameter on the `LINE(nnnn)` initialization statement specifies the address of the line you want to start.

After the line starts, the operator at either NJE node must issue the `$$ N` command to specify the name of the BSC line and any password information required to make the connection. If a dedicated line exists but is drained, it will be started automatically and a connection attempted by the `$$ N,N=` node command. For a BSC connection, the `$$ N` command directly invokes the NJE network path manager. If the other end of the line is started, the connection is made.

## Starting SNA Dynamic Connections

For an SNA NJE session, you must define a logical SNA line; that is, you must have added `UNIT=SNA` on the `LINE(nnnn)` initialization statement. If the line is not dedicated, (no `LINE=` parameter specified on either the `NODE(nnnn)` or `APPL(avvvvvvv)` initialization statement), an operator must enter a `$$ LINE(nnnn)` command to start the line before attempting to establish any SNA connections.

After the line starts, an operator at either NJE node issues a start networking (`$$ N`) command to initiate an SNA NJE application-to-application session. When entering the `$$ N` command, the operator can specify one of two names to identify the other node:

- The unique application name (on the `A=` parameter) by which VTAM knows JES2 at the other end. (The JES2 LOGON(1) initialization statement at the other node uses the application name to identify JES2 as a cross-domain resource to VTAM.)
- The node name if only one application exists at that node.

If a dedicated line exists but is drained, it will be automatically started by the `$$ N` command. For SNA application-to-application sessions, JES2 invokes the path manager after VTAM establishes the SNA session.

## SMF Record Summary: NJE (Network Job Entry) Processing

The following lists the SMF records written during JES2 NJE processing. For a complete list of the record contents, see *z/OS MVS System Management Facilities (SMF)*.

Table 59. SMF Records Used by JES2 NJE

| Record Number | Action that Causes the Record to be Written                                 |
|---------------|-----------------------------------------------------------------------------|
| 55            | A signon record is written at each node ( <code>\$\$ N(n)</code> commands). |
| 56            | Whenever a sign-on attempt contains an incorrect line or node password.     |
| 57            | To record SYSOUT information.                                               |
| 58            | The records written at each node whenever a networking session is ended.    |

## The Path Manager

JES2 systems have a feature called the network path manager; other IBM networking packages (for example, JES3 and RSCS) do not. The JES2 network



path manager maintains path information for all connections between NJE members (nodes). Each JES2 member of the NJE network has a copy of the path manager. The path manager determines the best paths to the various nodes and maintains information about the status of the network.

Path manager processing is essentially the same for both SNA and BSC NJE. Each path manager can have a consistent picture of the network at any given point in time. As nodes make and break connections in the network, the path managers at the various nodes broadcast their views of the network through Network Connection Control (NCC) records to directly attach nodes and update internal routing tables based on the information they receive. The path manager issues the \$HASP500 message when various NJE sign-on and connectivity problems occur. See *z/OS JES2 Messages* for the list of associated reason codes and their meanings.

### Network Connection Control Records

The path manager sends Network Connection Control (NCC) records between JES2 nodes to establish NJE connections and keep track of non-adjacent connections. The path manager uses the NCC records to update the path manager routing tables that establish the path manager's view of the network. These network updates occur through the **M** and **N** records that add and subtract members from a network, respectively.

The path manager determines the *best path* based upon the *path of least resistance* between the local node and each other node in the network. The resistance is derived from NCC records, CONNECT initialization statements, and parameters on the NJEDEF, NODE(nnnn), APPL(avvvvvvv), and LINE(nnnn) initialization statements. For more information on how the path manager uses these specifications for both adjacent and non-adjacent connections, see "Determining Path Resistance" on page 301.

The following is a list of the network connection control records. Only JES2 uses those records denoted by an asterisk (\*).

| Record   | Purpose              |
|----------|----------------------|
| <b>I</b> | Initial Sign-on      |
| <b>J</b> | Response Sign-on     |
| <b>K</b> | Reset Sign-on*       |
| <b>L</b> | Concurrence sign-on* |
| <b>M</b> | Add Connection*      |
| <b>N</b> | Subtract Connection* |
| <b>B</b> | Signoff              |

Note that the path manager does not send records about the following connections:

- Predefined or static connections (using a CONNECT initialization statement)
- Non-path manager connections
- Private connections

Non-JES2 nodes (such as JES3, RSCS, and AS/400) discard NCC **M** and **N** records.

See "Displaying Information About a Network" on page 287 for an example of how to display all active paths to a node.

### Non-Path Manager Connections

You can identify nodes that do not have a path manager (non-JES2 nodes) by coding PATHMGR=NO on the NODE(nnnn) initialization statement. You can also

specify that an adjacent node is not to receive any NCC add and subtract records by specifying PATHMGR=NO on NODE statement for that node.

Note that JES2 can establish a connection between two NJE nodes using either path manager protocols or non-path manager protocols. However, **both nodes must use the same protocols or the connection will not complete.** In these instances, JES2 issues a \$HASP500 message at one or both ends of the connection to explain why the connection failed.

**Non-Path Manager Protocol:** In the network illustrated in Figure 65, the JES2 WASH node initiates a non-path manager sign-on with the non-JES2 NEWYORK node. (Either node can initiate non-path manager sign-on.)




Figure 65. Sign-On Between Two Nodes Using Non-Path Manager Protocol

1. WASH attempts to sign-on to NEWYORK by sending an **I** (initial sign-on) record.
2. NEWYORK responds to WASH by sending a **J** (response sign-on) record.

(The **I** and **J** records can contain both node and BSC line passwords.)

**Full Path Manager Protocol Within a Network:** The example in Figure 66 shows two path manager nodes connecting using SNA protocols, or BSC protocols when the "high end" (node name closer to "Z" in the alphabet) initiates the protocol.




Figure 66. Two Path Manager Nodes Sign-on Protocol

1. WASH attempts to sign-on to NEWYORK by sending an **I** (initial sign-on) record.
2. NEWYORK responds to WASH by returning a **J** (response sign-on) record.
3. WASH responds to NEWYORK by returning an **L** (concurring sign-on) record to indicate that both systems will communicate across the established line.

- Once connected, both WASH and NEWYORK send **M** (add connection) and **N** (subtract connection) records to each other to share information about their other NJE connections. They also send **M** records to other path manager nodes to which they are connected to notify them of this connection.

When this connection is dropped by either WASH or NEWYORK, both nodes send **N** records to any path manager nodes with which they are connected to inform them that the connection no longer exists.

In the BSC case where the “low end” initiates the sign-on, the “low end” responds to the **J** record with a **K** record and the “high end” sends the **L** record.

## Private Connections

A private connection exists when two nodes in a network do not pass NCC records to other nodes to inform them of the connection. You might want to define a private connection if your node has limited spool space and you would like to reserve this spool space only for communication with an adjacent node.

You can suppress information from reaching the rest of the network about a connection between your node and an adjacent JES2 node from Version 4 or any later release by specifying PRIVATE=YES on the NODE(nnnn) initialization statement.

Note that you must specify both ends of a connection as PRIVATE=YES on the NODE(nnnn) initialization statements to ensure that the path manager does not send NCC records.

In Figure 67, only nodes A6 and B5 know about their 'private' connection.




Figure 67. Two Private Nodes Across Subnets

To suppress information about a connection between your node and an adjacent non-JES2 node or an adjacent JES2 node that is not Version 4 or a later release, specify NODE PATHMGR=NO on your node and specify a CONNECT statement at the pre-Version 4 JES2 node.

### Summary of PATHMGR= and PRIVATE= Parameters

The following table summarizes the possible settings of the PATHMGR= and PRIVATE= parameters on the NODE(nnnn) initialization statements and their effects.

Table 60. *NODE(nnnn) Statement - PATHMGR= and PRIVATE= Parameter Specifications*

| Node Location | Operating System                                                                | PATHMGR=                                                                            | PRIVATE=                                                                                              |
|---------------|---------------------------------------------------------------------------------|-------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------|
| Own Node      | JES2 Version 4 or a later release                                               | Not applicable                                                                      | NO<br><br>YES to prevent sending NCC records about your member-to-member connections within a MAS.    |
| Adjacent      | JES2 Version 4 or a later release                                               | YES<br><br>NO to make private and keep from sending Path Manager NCC records to it. | NO<br><br>YES to keep other nodes from finding out about this connection                              |
| Adjacent      | JES2 pre-Ver.4 node without a CONNECT initialization statement at the other end | YES must be specified                                                               | NO should be specified (YES only makes it private at this end - the other node will send NCC records) |
| Adjacent      | JES2 pre-Version 4 node with a CONNECT initialization statement at their end    | NO must be specified                                                                | not applicable (PATHMGR=NO makes it private)                                                          |
| Adjacent      | non-JES2                                                                        | NO must be specified                                                                | not applicable (PATHMGR=NO makes it private)                                                          |
| Non-adjacent  | JES2                                                                            | YES should be specified                                                             | not applicable                                                                                        |
| Non-adjacent  | non-JES2                                                                        | NO should be specified                                                              | not applicable                                                                                        |

## Static Connections

Static connections, which are always private connections, are predefined through a CONNECT statement. These connections are useful to supplement or override the dynamic connections created by the JES2 path manager. A CONNECT statement can be used to:

- Specify remote connections that exist but the NCC M and N records cannot reach the local node because of intervening non-path manager nodes.
- Indicate that a connection should be assumed to be there by the path manager even if it is not really there.
- Override the resistance of the connection calculated by the path manager. (See “Determining Path Resistance” on page 301 for details.)

A connection involves 2 points in a network. Each point is the smallest addressable piece of the network. For Version 5 nodes, each point is a MAS which may contain multiple members. For pre-Version 5 nodes, each point is a single JES2 member. A CONNECT statement specifies 2 points that are to be connected. Each point is identified by its node and member number.

Any CONNECT statement involving a JES2 Version 5 node must specify a member number of 1 for that Version 5 node. This is because the smallest addressable point in a Version 5 node is a MAS. For pre-Version 5 nodes, because each member is a point in the network, you must specify the member number associated with the member to which you are connecting.

Use the MEMBERA= and MEMBERB= parameters to refer to various members of the shared spool (on the nodes defined by the NodeA= and NodeB= parameters) involved in the connection. The MEMBERB= parameter has the same meaning for

NodeB as the MEMBerA= has for NodeA. Prior to Version 5, the values coded for MEMBerA= and MEMBerB= corresponded to the MASDEF SID(n) parameter specified for the member.

Figure 68 shows that nodes 1 and 2 have a static connection because of the CONNECT statements in their initialization data sets. The statement appears below for ease of reference.

```
CONNECT NODEA=BOST1,MEMBERA=1,NODEB=NYC2,MEMBERB=1,REST=150
```

The NodeA= and NodeB= designations simply provide a means of specifying the two nodes which make up the connection (node 1 and node 2 in the example).




Figure 68. Static Connections

The REST= parameter specifies the total resistance of the connection between BOST1 (node 1) and NYC2 (node 2). When static connections involve pre-Version 5 job entry subsystems on the same node, set the resistance value to zero (see “Multi-Access Spool Configuration Considerations for NJE” on page 309).

Static connections are not propagated to other nodes, and are therefore private. A private connection is known only to those systems comprising the connection. If, in the example in Figure 68, the CONNECT statement appeared only in the initialization data sets for nodes 1 and 2, the connection is private and node 3 cannot reach node 1. Because the CONNECT statement describing the node 1-to-node 2 connection does appear among the initialization statements of some of the other nodes in the network, in this example, the connection is known to the nodes that have the CONNECT statement.

Specifying the CONNECT statement places an entry describing the connection in the path manager routing tables.

### Using the CONNECT Statement

The following table summarizes when it is appropriate to use a CONNECT initialization statement:

Table 61. *CONNECT Statement*

| Type of Connection                                    | CONNECT in the Local JES2 Version 4 or a Later Release<br>Initialization Data Set                                                                                                                       |
|-------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Between members on the local (OWNNODE) node           | Not Valid on Version 5<br>Omit on Version 4 releases                                                                                                                                                    |
| To an adjacent JES2 node                              | Use to override dynamic connection; otherwise omit                                                                                                                                                      |
| To an adjacent non-JES2 node                          | Use to override dynamic connection or override resistance; otherwise omit                                                                                                                               |
| Remote connection between two path manager nodes      | Use to define connection if the other node cannot send this node NCC records through other JES2 nodes. (that is, There is a non-path manager node between this node and the other node.) Otherwise omit |
| Remote connections between two non-path manager nodes | Required if they are in the same remote subnet.                                                                                                                                                         |

## Controlling Static Connections

Static connections can be added, deleted, modified, and displayed using the following commands.

- \$ADD CONNECT
- \$DEL CONNECT
- \$T CONNECT
- \$D CONNECT


For examples of how to use these commands, see “Displaying Information About a Network” on page 287.

## Preventing Looping When Using Connect Statements

Figure 69 on page 298 shows definitions for a 3-node network with one non-JES2 node (N3). Each of these connections has a resistance value defined to prevent transmitted data from looping through the system if multiple outages occur.

To understand the effect of simultaneous multiple outages on incorrectly defined connections in a network involving a non-JES2 node, assume that:

- The N1 to N3 and N2 to N3 connections are unavailable.
- N3 is a non-JES2 node.
- Only the connections listed exist.



```

N1
NODE(3) NAME=N3,PATHMGR=N0
 CONNECT NODEA=N2,NODEB=N3, REST=100
NJDEF RESTMAX=150

N2
NODE(3) NAME=N3, PATHMGR=N0
 CONNECT NODEA=N1, NODEB=N3,REST=100
NJDEF RESTMAX=150

```

*Figure 69. Three-Node Network Configuration CONNECT Statements to Avoid Looping*

The path managers at both N1 and N2 discover that the path to N3 is down. Both path managers attempt to route data to the alternate path. When data arrives at N2, the path manager there knows the N2 to N3 path has failed. Therefore N1 sends the data to N1 to make use of the N1 to N3 path. When data arrives at N1, the path manager there knows the N1 to N3 path has failed. Therefore, N1 sends the data to N2 to make use of the N2 to N3 path. The path managers continue to send the data back and forth (looping) until one of the unavailable links restarts or the MAXHOP= limit at one of the sites has been reached.

**Note:** In the case where both paths are prone to failure and require alternate paths, IBM recommends a low setting, such as MAXHOP=2. In the event of a failed connection, data travels back-and-forth only one time.

An installation can avoid looping by defining a RESTMAX= parameter value that eliminates all alternate paths, as shown in Figure 69. That is, the path from N1 through N2 to N3 has a total resistance of 200. Data from N1 will not take this path to N3 because the resistance exceeds the 150 maximum.

If one of the paths is particularly prone to failure, an installation can add static connections between both N1 and N3 and N2 and N3 as illustrated in Figure 70.

```

CONNECT NODEA=N1,NODEB=N3,REST=100
CONNECT NODEA=N2 NODEB=N3,REST=100

```

*Figure 70. CONNECT Statements that Avoid Looping in 3-Node Network*

The CONNECT statements advise the path managers at both N1 and N2 when the N3 connection is down, so both path managers hold the data.



**Note:** If both paths require alternate paths but CONNECT statements like those in Figure 70 on page 298 do not exist, IBM recommends a low setting for the MAXHOP= parameter (MAXHOP=2). In the event of a failed connection, data travels back-and-forth only one time.

## Defining and Communicating Between Subnets

A subnet is a set of nodes identified by name to simplify NJE routing tables by reducing NCC record traffic and path manager overhead. Networks consisting of many nodes become more manageable when you group nodes into subnets.

For example, when two corporations merge, it might be easier to manage nodes from each of the two corporations as separate subnets, with access to each other through nodes attached to each other through CONNECT statements. Such nodes are called gateway nodes. The path manager presumes that if one node in another subnet can be reached, all nodes in that subnet can be reached without additional resistance.

Figure 71 provides an example of two subnets named MD and NY. In this example, NYC and WASH are the gateway nodes for each of the subnets. Figure 72 on page 300 shows the initialization statements that define these subnets.




Figure 71. Example of Defining Subnets

```

/***** CONNECT STMT TO SUBNETS *****/
/*****
CONNECT NODEA=0005,NODEB=0006,MEMBA=1,MEMBB=1,REST=10
/***** NJE NODE DEFINITIONS DEFINING SUBNETS *****/
/*****
NODE(1-10) AUTH=(NET=YES),TRACE=YES
NODE(01) NAME=WHETN,PATHMGR=YES,SUBNET=MD
NODE(02) NAME=GBURG,PATHMGR=YES,SUBNET=MD
NODE(03) NAME=BELAIR,PATHMGR=NO,SUBNET=MD
NODE(04) NAME=DEL,PATHMGR=NO,SUBNET=MD
NODE(05) NAME=WASH,PATHMGR=NO,SUBNET=MD
NODE(06) NAME=NYC,PATHMGR=NO,SUBNET=NY
NODE(07) NAME=POK,PATHMGR=NO,SUBNET=NY
NODE(08) NAME=KGN,PATHMGR=NO,SUBNET=NY
NODE(09) NAME=TRYTN,PATHMGR=NO,SUBNET=NY
NODE(10) NAME=ALBANY,PATHMGR=NO,RECEIVE=JOBS,SUBNET=NY
/*****

```

Figure 72. Example of Subnets Defined in the Initialization Data Set

These definitions must be in the initialization data set of each node involved in order to define a subnet. To prevent confusion, IBM recommends using different naming conventions for subnets than those used for nodes. For example, if all nodes in a network begin with the prefix 'ND', use a different prefix for the names of subnets in your network.

Use the SUBnet= parameter on the NODE(nnnn) initialization statement to define the subnet to which a node belongs. Then, use one (or more) of the nodes in a subnet as the gateway to that subnet. That node communicates to the gateway node in another subnet. Any node with which you establish a connection to a node in another subnet becomes a gateway node. You might want to use more than one node as the gateway depending on factors such as the number of nodes in a subnet, or the communication needs between subnets. Note, however, that the fewer gateway nodes that are used, the more manageable the communication between subnets becomes.

Because you cannot define the subnets on all nodes in a network simultaneously, you must specify them carefully. Ensure that nodes outside your subnet have your subnet defined before nodes inside your subnet define it. Then define all subnets consistently throughout the network, so that all nodes have a valid view of routing.

You can exercise control over subnets through JES2 operator commands, which allow you to:

- Add nodes to a subnet or change nodes from one subnet to another by using the \$T NODE(nnnn) command.
- Change the static connections using the \$ADD, \$DEL, and \$T CONNECT commands.
- Display a list of nodes in one or more subnets using the display subnet(s) (\$D SUBNET) command.

**\$D SUBNET(M\*)**

```
$HASP816 SUBNET(MD) WHETN, GBURG, BELAIR, DEL, WASH
```

For more information about using these commands, see “Displaying Information About a Network” on page 287 and *z/OS JES2 Commands*.

## Determining Path Resistance

Path resistance is a value set by an installation to control the flow of work between nodes in a network. The *best path* is determined by the JES2 path manager facility based on the path of least resistance. The resistance is derived from NCC records, CONNECT initialization statements and parameters on the NJEDEF, NODE(nnnn), APPL(avvvvvvv), and LINE(nnnn) initialization statements.

When defining resistance for a path, you should base the values on the line speed (the faster the line, the lower the line resistance) and the expected workload (the lighter the workload, the lower the work resistance).

The following describes how to:

- Calculate resistance for adjacent connections
- Calculate resistance for non-adjacent connections
- Limit store-and-forward transmissions.

### Calculating Resistance for Adjacent Connections

Table 62 summarizes how JES2 calculates path resistance for adjacent connections. The parameters that the JES2 path manager uses to calculate resistance varies depending on the connection type as follows:

*Table 62. Resistance Calculation for Adjacent Connections*

| Connection Type                          | Partial Resistance from Local Definitions                                 | Partial Resistance from Non-local Definitions<br>(Unless SENTREST=IGNORE is specified on the NODE (nnnn) statement.) |
|------------------------------------------|---------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------|
| Dynamic SNA Connection to JES2           | NJEDEF RESTNODE + APPL or NODE REST                                       | NJEDEF RESTNODE + APPL or NODE REST                                                                                  |
| Dynamic BSC Connection to JES2           | NJEDEF RESTNODE + LINE REST                                               | NJEDEF RESTNODE + LINE REST                                                                                          |
| Dynamic Connection to JES3 or POWER Node | NJEDEF RESTNODE + LINE, APPL or NODE REST                                 | 0                                                                                                                    |
| Dynamic Connection to VM or AS/400       | NJEDEF RESTNODE + LINE, APPL or NODE REST                                 | 200                                                                                                                  |
| Static Connection                        | CONNECT REST= value (overrides any dynamic resistance as described above) |                                                                                                                      |

Use the following formula to calculate the resistance of a connection to an adjacent node without a CONNECT statement:

**From Node A**      $R = RL_a + RW_a + NCCIREST$

**From Node B**      $R = RL_b + RW_b + NCCIREST$

KEY:

R            - represents total resistance  
RLx        - represents the resistance of the line (BSC) or session (SNA)  
RWx        - represents the resistance through the node  
NCCIREST - represents the partial resistance sent by the other node


*Figure 73. Formula for Calculating the Resistance of Adjacent Nodes.*

**Notes:**

1. NCCIREST consists of the combined resistance of the line plus the JES2 workload as determined by the node at the other end of the connection.
2. Neither node can control the line or workload resistance specified by the other node. For ways of limiting the impact of another node's resistance, see "Path Selection Considerations" on page 305.
3. Two nodes must first exchange their partial resistance values to establish the total resistance of a connection. The partial resistance is the sum of the resistance of the line plus the resistance caused by workload as determined by each node. The exchange occurs as follows:
  - a. The node that initiates the connection sends its partial resistance to the other node using an NCC I (initial sign-on) record.
  - b. The other node returns its partial resistance using an NCC J (response sign-on) record.
  - c. If path manager is active, the total resistance of the connection is sent back and forth in the NCC K (reset) and the NCC L (concurrence) records, respectively.

For example, when defining the 3-node connection shown in Figure 74 on page 303, an installation would base the resistance of the BSC connection between NEWYORK and BOSTON using line 3 using these variables:

| Variable   | Description                                                                                                                                                                                                      |
|------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>RLa</b> | Represents the resistance of the line as evaluated by the installation manager at node "a" (NEWYORK in the following example). This is the value specified on NODE A's REST= parameter on the LINE(3) statement. |
| <b>RLb</b> | Represents the resistance of the line as evaluated by the installation manager at node "b" (BOSTON in the following example). This is the value specified on NODE B's REST= parameter on the LINE(3) statement.  |
| <b>RWa</b> | Represents the resistance due to workload on JES2 as evaluated by the installation manager at node "a". This is the value specified on NODE A's RESTNODE= parameter on the NJEDEF statement.                     |
| <b>RWb</b> | Represents the resistance due to workload on JES2 as evaluated by the installation manager at node "b". This is the value specified on NODE B's RESTNODE= parameter on the NJEDEF statement.                     |



### NEWYORK1 (NODE 1)

```
NJEDEF NODENUM=3,LINENUM=2,OWNNODE=1,PATH=2,RESTNODE=50,RESTMAX=250,
 RESTTOL=30
NODE(1) NAME=NEWYORK1
NODE(2) NAME=WASHDC2,REST=20
NODE(3) NAME=BOSTON3
LINE(1) UNIT=SNA
LINE(3) REST=100,TRANSPAR=YES
LOGON(1) APPLID=NEWYORK1
```

### WASHDC2 (NODE 2)

```
NJEDEF NODENUM=3,LINENUM=3,OWNNODE=2,PATH=2,RESTNODE=50,RESTMAX=250,
 RESTTOL=10
NODE(1) NAME=NEWYORK1,REST=20
NODE(2) NAME=WASHDC2
NODE(3) NAME=BOSTON3
LINE(1) UNIT=SNA
LINE(2) REST=20,TRANSPAR=YES
LINE(5) REST=20,TRANSPAR=YES
LOGON(1) APPLID=WASHDC2
```

### BOSTON3 (NODE 3)

```
NJEDEF NODENUM=3,LINENUM=3,OWNNODE=3,PATH=2,RESTNODE=50,RESTMAX=250,
 RESTTOL=10
NODE(1) NAME=NEWYORK1
NODE(2) NAME=WASHDC2,REST=20
NODE(3) NAME=BOSTON3
LINE(2) REST=20,TRANSPAR=YES
LINE(3) REST=100,TRANSPAR=YES
LINE(5) REST=20,TRANSPAR=YES
```

Figure 74. Path Resistance Values

For the SNA connection in Figure 74, the resistance between NEWYORK1 and WASHDC2 (using line 1) is calculated with the following variables:

| Variable   | Description                                                                                                                                                                             |
|------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>RLa</b> | Represents the resistance of the session as evaluated by the installation manager at node “a” (NEWYORK1 in the previous example). This is the value specified on the REST= parameter of |

NEWYORK1's APPL(WASHDC2) initialization statement. If APPL(WASHDC2) is omitted, resistance is obtained from the REST= parameter in the NODE(nnnn) initialization statement for WASHDC2.

- RLb** Represents the resistance of the session as evaluated by the installation manager at node "b" (WASHDC2 in the previous example). This is the value specified on the REST= parameter of WASHDC2's APPL(NEWYORK1) initialization statement. If APPL(NEWYORK1) is omitted, resistance is obtained from the REST= parameter in the NODE(nnnn) initialization statement for NEWYORK1.
- RWa** Represents the resistance due to workload on JES2 as evaluated by the installation manager at node "a". This is the value specified on NODE A's RESTNODE= parameter on the NJEDEF statement.
- RWb** Represents the resistance due to workload on JES2 as evaluated by the installation manager at node "b". This is the value specified on NODE B's RESTNODE= parameter on the NJEDEF statement.

Using values from Figure 74 on page 303, you would calculate the total resistance for these connections as follows:

NEWYORK1 to WASHDC2 (line 1):  $R = 20 + 20 + 50 + 50 = 140$   
 WASHDC2 to BOSTON3 (line 2):  $R = 20 + 20 + 50 + 50 = 140$   
 NEWYORK1 to BOSTON3 (line 3):  $R = 100 + 100 + 50 + 50 = 300$

If parallel lines with different resistance values connect two nodes (for example, lines 2 and 5 in Figure 74 on page 303), JES2 uses the lower resistance value when determining the best path.

You can use the SENTREST= parameter on the NODE(nnnn) initialization statement to ignore the partial resistance sent by another node (in the NCC I and NCC J records). SENTREST= allows you to specify whether another node's resistance should be added to the local node's to determine resistance at the local node. If you specify SENTREST=IGNORE, the local node ignores the resistance sent from the connecting node. This value allows the local node to control the resistance sent during sign on processing. You can specify SENTREST=IGNORE for only non-path manager nodes.

For example, if NEWYORK1 in Figure 74 on page 303 were a VM node, BOSTON3 can maintain a local resistance of the NEWYORK1-to-BOSTON3 connection of 150 by refusing to accept the partial resistance from NEWYORK1.

## Calculating Resistance for Non-Adjacent Nodes

Use Table 63 to calculate total resistance between non-adjacent nodes.

*Table 63. Resistance Determination for Non-Adjacent Connections*

| Connection Type                                         | Total Resistance                                                       |
|---------------------------------------------------------|------------------------------------------------------------------------|
| Path to a node within our subnet (or not in any subnet) | Sum of the individual connections in that path                         |
| Path to a node not in the local subnet.                 | Sum of the connections between subnets in that path                    |
| Static Connection                                       | CONNECT REST= value (overrides any dynamic resistance described above) |
| Two nodes in the same remote subnet                     | 0                                                                      |

In Figure 74 on page 303, the resistance from NEWYORK1 to BOSTON3 through lines 1 and 2 would be calculated as follows:

RESISTANCE FROM NEWYORK1 to WASHDC2 (line 1) = 140  
RESISTANCE FROM WASHDC2 to BOSTON3 (line 2) = 140

---

TOTAL RESISTANCE NEWYORK1 to BOSTON3 = 280

Although line 3 is a direct path between NEWYORK1 and BOSTON3 as shown in Figure 74 on page 303, the path through WASHDC2 (over lines 1 and 2) actually have a lower resistance, making it the best path. No data will be sent over line 3 unless you instruct JES2 to use multiple paths by setting the RESTOL= and PATH= parameters on the NJEDEF initialization statement as described in “PATH” on page 306.

### Controlling Store-and-Forward Transmissions

You can force JES2 to:

- Use only direct connections to send data to another node
- Use only direct connections to send data to a specific node
- Prevent the use of a specific node as an intermediate node.

**Using only Direct Connections to Send Data to Another Node:** To restrict all NJE transmissions to use only direct connections and not use any indirect routing paths, specify RESTMAX=0 on the NJEDEF initialization statement. Specifying RESTMAX=0 limits path selection to adjacent nodes and nodes whose total path resistance is 0.

**Using Only Direct Connections to Send Data to a Specific Node:** If you have files destined for an adjacent node that are too large (or highly sensitive), you might want to prevent any alternate path routing if the link is down or backed up with other work. To prevent files from being sent through intermediate nodes, specify REST=0 on a CONNECT initialization statement that defines the connection. This will override the path manager’s attempt to use an alternate path unless you have NJEDEF PATH greater than 1 and the alternate path’s resistance is less than RESTTOL.

**Preventing the Use of a Specific Node as an Intermediate Node:** If you have adjacent nodes that have limited capacity or that are not trustworthy to safely store and forward NJE files, you might want to restrict their ability to be an intermediate node to other nodes in your network:

- Specify a high resistance for the node (a value higher than RESTMAX).
- Isolate the node from the other nodes through subnets and non-path manager protocols.
- Specify ENDNODE=YES on the NODE(nnnn) initialization statement.

Specifying ENDNODE=YES prevents a node from being eligible to store-and-forward work.

## Path Selection Considerations

You can use the NJEDEF initialization statement to affect how JES2 selects paths throughout a network. Use the following parameters to specify alternate paths to a node and influence how JES2 determines those paths:

- PATH=
- RESTTOL=
- RESTMAX=



- SENTREST=

### **PATH**

Specify this parameter if you maintain more than one path to a destination. For example, in Figure 74 on page 303, you must specify PATH=2 on the NJEDEF statement if NEWYORK1 uses both paths to BOSTON3. The network path manager maintains the number of paths to a given destination that is specified on the PATH= parameter. If an installation specifies two paths to a node, the network path manager first checks to see if both paths are within the limits of the RESTTOL= parameter. If one is not, the path manager does not select this path. However, if both paths are within the limits of RESTTOL=, an installation cannot predict which path the path manager will choose.

### **RESTTOL**

This parameter specifies the maximum difference in resistance between the best possible path and an acceptable alternate path. For example, based on the calculation of the resistances of the two possible paths between NEWYORK1 and BOSTON3 (Figure 74 on page 303), the path through lines 1 and 2 (with a total resistance of 280) is the best path. Since 30 is the RESTTOL= value, data cannot travel through line 3 because the resistance of 300 exceeds the RESTMAX= parameter value. (See the following description of the RESTMAX= parameter.)

The value of RESTTOL= must be less than the resistance between any two nodes in the network; otherwise, jobs and messages will transmit in an erratic fashion.

### **RESTMAX**

This parameter allows you to control the storing-and-forwarding of data throughout your network. RESTMAX= specifies the maximum resistance through which JES2 attempts to transmit work for both adjacent and non-adjacent nodes. To avoid inconsistencies in the views of the network maintained by the various path managers, specify the same value for RESTMAX= at all nodes.

To prevent store-and-forward through any nodes in a network, specify a low value on this parameter. This value restricts all NJE connections to direct connections, eliminating direct routing paths. RESTMAX=0 ensures that data is sent to an adjacent node only, and never to an intermediate node from which it can be forwarded to a final destination. If you specify RESTMAX=0, JES2 considers the direct path to any adjacent node usable, no matter what resistance is coded. Nodes beyond the adjacent node are reachable only if the total resistance to them is zero, or they exist in the same subnet as an adjacent node.

In Figure 74 on page 303, the value specified for RESTMAX= at WASHDC2 (RESTMAX=250) prevents WASHDC2 from transmitting to NEWYORK1 through BOSTON3, even if line 1 is down, because the total resistance of the connection is 440. Because the RESTMAX= parameter applies to adjacent and non-adjacent nodes, NEWYORK1 cannot transmit to BOSTON3 over line 3 because the resistance is 300.

## **Extending Network Capability**

The network illustrated in Figure 75 on page 308 shows how you can extend the capability of basic BSC and SNA NJE configurations. These initialization statements enable an installation to determine the security access one node has to another, the job numbers specified at each node, as well as the destinations for all output jobs and SYSOUT. Individual nodes must share definitions for the capabilities defined through these initialization parameters to ensure the regular flow of traffic throughout a network.

Refer to Figure 75 on page 308 as you read through the following explanation of the various initialization statements that control the networking connections between NEWYORK and WASHDC. Preceding each of the following statements there is a number in parentheses that correlates to a highlighted statement number in the figure.

#### **1** NODE(1) NAME=NEWYORK, PASSWORD=SECRET

This statement assigns the name NEWYORK to this node. When node 1 attempts to sign on to another node in the network, it will identify itself as NEWYORK. The receiving node will look up the name NEWYORK to determine if NEWYORK is a member of the network. If the receiving node does not find an entry for NEWYORK, the receiving node will reject the sign-on.

PASSWORD=SECRET specifies that if no SEND= password value is specified for NODE(1) to send to another node to which it is signing on, NODE(1) will send this password to that node instead. Note that this option is provided only for compatibility with previous releases of JES2. If you have defined all your nodes using PASSWORD=(SEND=word1,VERify=word2), then it would not be necessary to specify a PASSWORD= parameter on the NODE(1) definition in this initialization data set.

#### **2** NODE(2) NAME=WASHDC, PASSWORD=(SEND=SECRET,VER=HIDDEN)

PASSWORD=(SEND=SECRET,VER=HIDDEN) specifies that the password that NEWYORK will send to WASHDC is SECRET. The node WASHDC will use this password for verification during sign-on. In WASHDC's initialization data set, the NODE(1) initialization statement must specify PASSWORD=(SEND=HIDDEN,VER=SECRET).

If NEWYORK does not supply the password SECRET when attempting to sign-on to node WASHDC, node WASHDC rejects the sign-on attempt. WASHDC will place the password HIDDEN in the response to the sign-on record that it sends to NEWYORK. If WASHDC does not supply the password HIDDEN, NEWYORK stops sign-on record processing. If the connection is an SNA session over line 2, the processing described takes place after VTAM establishes a session between the two NJE nodes.

**Note:** The initialization data set should be protected to prevent disclosing passwords contained on NODE(nnnn) initialization statements. If RACF is used, provide protection by specifying UACC=NONE for the data set.




Figure 75. An Expanded Network

### 3 AUTH=(NET=YES)

Specifies one of the four authority categories. In the example, the specification of NET=YES in the AUTH= parameter on the NODE(2) initialization statement on NEWYORK for WASHDC indicates WASHDC has the same authority as consoles attached locally to NEWYORK. WASHDC also has (by default) the ability to affect jobs (JOB=YES), the ability to affect devices (DEVICE=YES), and the ability to affect system function (SYSTEM=YES) at NEWYORK. You can override these defaults. For example, NODE2's initialization data set restricts NEWYORK from affecting system function (AUTH=SYS=NO) at WASHDC.

### 4 LINE(1) PASSWORD=LINEPSWD

Specifies the password associated with the line connecting nodes 1 and 2. Notice that both nodes include the password specification in their line definition initialization parameters. NEWYORK will include the line password in the initial sign-on record sent to WASHDC. WASHDC verifies the line password and sends a response record to NEWYORK that also includes the line password that NEWYORK verifies before continuing sign-on record processing.

### 5 JOBDEF RANGE=(1-499)

Node 1 will assign job identifiers beginning at 1 and assign no identifier greater than 499 for jobs originating locally. For jobs received from node 2 for execution at node 1, node 1 attempts to assign the JOBID that appears in the NJE header received from node 2. Because of the JOBDEF RANGE= specification at node 2, jobs originating at node 2 will have job identifiers beginning at 500 up to and including 65534. Because node 1 does not assign identifiers higher than 499, it can assign numbers beginning at 500 and ending at 65534 (the JES2 system default for job identifiers) to jobs received from node 2. Consequently, each job identifier is unique, and a job transmitted from node 1 to node 2 will have separate job identifiers at each node.

## **6 RDR(1) PRTDEST=NEWYORK**

Indicates that NEWYORK will print normal print output produced by jobs read in at RDR1 in WASHDC. The PRTDEST=NEWYORK specification corresponds to the NODE 1 node definition statement as defined at node WASHDC. If no NODE 1 statement has been specified at node WASHDC, a printer attached to the system specified by OWNNODE= is the default printer (WASHDC in this example).

## **7 DESTID(BRONX)**

The statement assigns the name BRONX to the remote workstation numbered 1 (RMT1) attached to NODE1. You can now use BRONX to send jobs or data to the remote workstation.

# **Adding a Node to an Existing Network**

The network illustrated in Figure 74 on page 303 is more complex than those examined thus far. It introduces some of the initialization parameters that influence path selection. The addition of BOSTON (node 3) to the network requires you to update the initialization statements for NEWYORK and WASHDC as follows:

- Add a NODE(nnnn) NAME=BOSTON statement to define BOSTON, and on this initialization statement, include a PASSWORD=(SEND=word1,VER=word2) parameter to define unique passwords between BOSTON and the other two nodes.
- Add 1 to the NODENUM= parameter on the NJEDEF statement.

In the network in Figure 74 on page 303, there are three possible connections:

- NEWYORK to WASHDC (line 1)
- NEWYORK to BOSTON (line 3)
- WASHDC to BOSTON (lines 2 and 5)

The parallel lines between WASHDC and BOSTON do not represent a separate connection. This link is simply an alternate line to an adjacent node.

---

# **Multi-Access Spool Configuration Considerations for NJE**

A multi-access spool configuration (MAS) can participate in the JES2 network. JES2 considers the spool and its attached members to be one NJE network node. However, the parameters used to define JES2 members that share a spool can affect the performance of the network (see “Queueing Messages to a Multi-Access Spool Node” on page 311).

The following describes:

- An example of JES2 specifications required on a MAS node (BSC or SNA)

- JES2 specifications that can affect network performance
- An example of JES2 specifications particular to a MAS SNA node.

## Example of a Multi-Access Spool Node

All JES2 members of a multi-access spool node must specify the same value for the OWNNODE= and NODENUM= parameters on the NJEDEF statement in each of their initialization data sets. They must also have identical node definition parameters as specified on the NODE(nnnn) initialization statement, including the node name.

In the network in Figure 76, node 2 is a multi-access spool configuration with the symbolic name WASHDC. There are 2 members active on node 2 (SYSA and SYSB), each of which has an active NJE line to node 1 (NEWYORK).




Figure 76. Multi-Access Spool Configuration (BSC)

### Processing When WASHDC is a Version 5 Node

In this configuration, there is one NJE connection between node 1 and node 2. This connection connects NEWYORK member 1 with WASHDC member 1. There are two active NJE links for one NJE connection; this is considered a multi-trunk connection. The link with the lower resistance is considered to be the primary trunk. In Figure 76 on page 310, line 2 is the primary trunk because its resistance (60) is less than line 1's resistance (70). The resistance of the primary trunk (60) is associated with the NJE connection that is sent into the network. Data is sent on whatever link is available.

### Processing When WASHDC is a Pre-Version 5 Node

In this configuration, there are 3 NJE connections. This is because prior to JES2 version 5, each member of the MAS used the member number corresponding to its member identifier, MASDEF SID(n), when establishing an NJE connection. The 3 connections that exist in Figure 76 on page 310 are:

- node NEWYORK member 1 to node WASHDC member 1
- node NEWYORK member 1 to node WASHDC member 2
- node WASHDC member 1 to node WASHDC member 2

The connection between WASHDC members 1 and 2 is established automatically when the second member is started.

When connecting to a pre-version 5 JES2 MAS, resistance considerations determine which link is used to transmit job and SYSOUT. Jobs and SYSOUT are routed to a node not a member. In Figure 76 on page 310, there are 2 NJE connections between node NEWYORK and node WASHDC and thus 2 paths. Data is sent over the path of least resistance. With the specifications listed in Figure 76 on page 310, data from WASHDC to NEWYORK or NEWYORK to WASHDC will be sent on either line 1 or line 2.

If PATH= on NJEDEF were allowed to default to 1, data would only be sent over line 2 which has a lower resistance (60) than line 1 (70). If at NEWYORK, the value for RESTTOL= on NJEDEF were allowed to default to 0, data traveling from NEWYORK to WASHDC would not use line 1 because the difference in resistance between line 1 and line 2 would be 10 which is greater than RESTTOL=.

## Queueing Messages to a Multi-Access Spool Node

Optionally, you can direct commands and messages to a particular JES2 member attached to the spool. Use \$NnnnMmm to route a command to a specific member, where mm is the member number as defined on the MEMBER(mm) statement.

The MASMSG= parameter on the CONDEF statement specifies the maximum number of commands or messages that can queue between any two members of the multi-access spool configuration before the network discards messages. This count also applies to the number of input messages or commands a member can queue to itself.

When a member of a multi-access spool node queues a message to another member of that node, there is no interrupt mechanism to inform the receiving member that a message exists. The receiving member periodically reads the shared job queue record and examines queue information for new messages. The following JES2 initialization parameters control the length of time it takes for the receiving member to recognize the queuing. You specify the parameters (HOLD= and DORMANCY=) on the MASDEF initialization statement, and specify (DELAY=) on the NJEDEF statement. The \$T operator command can modify each of these parameters to make it easier to tune your multi-access spool node.

You should experiment to determine the parameter values that yield satisfactory responsiveness without causing adverse increases in system overhead for the individual nodes. Figure 76 on page 310 shows examples of these parameters. These values are for illustrative purposes and are *not* recommendations.

### MASDEF Queueing Parameters

The MASDEF statement defines various default values for a multi-access spool configuration. When a member of a multi-access spool configuration participates in a network, that member must have control of the shared queues before it can transmit or receive network data. The HOLD= and DORMANCY= parameters on MASDEF control the access to the shared queues by a member of the multi-access spool configuration. Careful consideration when specifying these parameters will help the performance of your communications within the network.

**HOLD:** Specifies the length of time the sending system holds the hardware reserve lock on the job queue. If the posting of work occurs early in the time slot represented by the HOLD= value, then the receiving system might not retrieve the job queue in its attempt to read because the sending system still holds the lock. Small values increase system overhead while increasing responsiveness to queuing.

**DORMANCY (mmmm,nnnn):** The mmmm value specifies the minimum length of time the receiving system will not consider requests to the job queue. This will also delay the sending system because it must own the job queue to queue the message. The nnnn value specifies the maximum length of time between requests for the job queue by the receiving system. Small values for both increase system overhead while increasing responsiveness to queuing.

### **NJEDEF Queueing Parameter**

The DELAY= parameter, on the NJEDEF statement, specifies the maximum delay time for intranodal message or command transmission. JES2 considers the value of the DELAY= parameter when transmitting commands and messages across the shared spool. If a job entry subsystem detects that the time specified in DELAY= is exceeded, it assumes a lockout has occurred. Too small a value can have adverse affects on spool use.

## **Defining a Multi-Access Spool Node (SNA Considerations)**

For SNA sessions, an installation must define each JES2 member attached to the MAS configuration as an application to VTAM. In addition, JES2 must supply unique application names that VTAM will use to identify JES2 through APPL(avvvvvvv) initialization statements. These considerations do not apply to BSC networks.

The application ID subscript (avvvvvvv) on the APPL statement that defines the JES2 member reading the initialization statement should correspond to the APPLID= on the LOGON(1) statement for that JES2. You can use a form of the APPLID= that is a variation of the node name qualified by multi-access spool member number.

Figure 77 shows samples of the initialization statements required for an SNA network, while adding a Node 3 (LA) to the two nodes (NEWYORK and WASHDC) shown in Figure 76 on page 310 for three NJE nodes, all of which are eligible for SNA sessions and one of which (WASHDC) is a MAS configuration. Notice that all nodes specify the APPL initialization statements defining the multi-access spool members at WASH specified. The APPL(avvvvvvv) initialization statements build identical application tables for each JES2.






Figure 77. Multi-Access Spool Configuration (SNA)



---

## Part 6. Remote Job Entry

|                                                             |     |
|-------------------------------------------------------------|-----|
| <b>Chapter 6. Remote Job Entry (RJE)</b>                    | 317 |
| Defining RJE Workstations to JES2                           | 318 |
| Planning for RJE Workstation System Growth                  | 319 |
| Defining RJE Devices                                        | 320 |
| Modifying RJE Workstations                                  | 321 |
| Recovering RJE Workstations from Failed Members             | 321 |
| SNA RJE Considerations                                      | 322 |
| VTAM LU and PU Parameters that Affect SNA RJE               | 322 |
| VTAM APPL Definitions for SNA RJE                           | 322 |
| SNA RJE Buffer Size                                         | 323 |
| Valid RU Sizes                                              | 323 |
| BSC RJE Processing                                          | 323 |
| BSC Multileaving Workstations Supported by JES2             | 324 |
| BSC Teleprocessing Buffer Considerations                    | 324 |
| SMF Record Summary: RJE Processing                          | 325 |
| Defining Lines for RJE Workstations                         | 325 |
| Nondedicated Lines                                          | 326 |
| RJE BSC Dial-Up Connections                                 | 326 |
| Dedicated Lines                                             | 326 |
| Defining BSC Lines for RJE Workstations                     | 327 |
| Defining SNA Lines for RJE Workstations                     | 329 |
| RJE Line Passwords                                          | 329 |
| Changing an RJE Workstation from BSC to SNA                 | 329 |
| Changing an RJE Workstation from SNA to BSC                 | 329 |
| Using Compaction on SNA RJE Workstations                    | 330 |
| How Compaction Works                                        | 330 |
| Starting and Stopping Remote Job Entry                      | 331 |
| Options for Disconnecting Remote Lines                      | 331 |
| BSC Workstations                                            | 331 |
| Format and Definitions for the /*SIGNON Statement           | 332 |
| Format for the /*SIGNOFF Statement                          | 332 |
| SNA RJE Workstations                                        | 332 |
| Initiating an Automatic Terminal Connection                 | 333 |
| Creating a SNA RJE Connection                               | 334 |
| Using the VTAM LOGON Command for SNA RJE                    | 334 |
| Using the VTAM LOGOFF Command for SNA RJE                   | 335 |
| JES2 RJE Bind Image                                         | 336 |
| Setting Line Density for RJE Devices                        | 337 |
| Altering the Sequence of Operations from an RJE Workstation | 337 |
| Pooling RJE Workstations                                    | 338 |
| Expanding RJE Workstations                                  | 338 |
| Consolidating RJE Workstations                              | 338 |
| Using CONDEST= to Specify the RJE Operator Console          | 339 |
| Remote Message Spooling                                     | 340 |



---

## Chapter 6. Remote Job Entry (RJE)

The JES2 **remote job entry (RJE)** function provides the ability to submit jobs and receive system output (SYSOUT) at remote facilities as if the jobs had been submitted at a local facility. In this chapter, the term **RJE workstation** or simply **remote** is used to indicate these RJE facilities. JES2 supports both **systems network architecture (SNA)** and **binary synchronous communication (BSC)** RJE workstations. JES2 RJE communication can use any of the following transmission protocols:

- BSC - that only allows the transmission of a single print or punch stream
- BSC multileaving - that simulates the transmission of multiple print and punch streams simultaneously
- SNA - that allows multiple print and punch streams simultaneously and accesses JES2 through VTAM.

The RJE workstations can be attached to JES2 by synchronous data link control (SDLC) or by a (point-to-point) BSC link. The RJE workstation becomes a logical extension of the local computer facility, and JES2 expects the RJE workstation to be controlled by a remote operator.

RJE workstations can include a processor such as a System/390. RJE workstations also support hardware terminals, multi-leaving BSC workstations, and SNA logical devices and can include **remote devices** (printers, punches, card readers, and a console).

An RJE workstation can also consist of a **remote terminal** that does not have a processor. A remote terminal, for example, a 2780 or 2770, can be used for entering jobs into and receiving data from JES2.

This chapter describes the following:

- “Defining RJE Workstations to JES2” on page 318.  
The JES2 initialization statements required to define an RJE workstation to JES2.
- “SNA RJE Considerations” on page 322.  
The JES2/VTAM connection that is required to use systems network architecture (SNA) protocols for RJE processing.
- “BSC RJE Processing” on page 323.  
The BSC protocols used in RJE processing, including a definition of multileaving and RMT generation.
- “SMF Record Summary: RJE Processing” on page 325.  
The SMF records written during RJE processing.
- “Defining Lines for RJE Workstations” on page 325.  
How lines must be defined at initialization for RJE processing.
- “Using Compaction on SNA RJE Workstations” on page 330.  
The SNA feature that increases the efficiency of data transmission by compressing master character pairs.
- “Starting and Stopping Remote Job Entry” on page 331.  
The JCL statements and their syntax required to begin and end RJE processing.
- “JES2 RJE Bind Image” on page 336.  
The VTAM statements and the corresponding JES2 parameters that create the bind image that JES2 uses to communicate with remote devices.

- “Altering the Sequence of Operations from an RJE Workstation” on page 337.  
How a remote operator or the JES2 systems programmer can control how SYSOUT is printed at an RJE workstation.
- “Pooling RJE Workstations” on page 338.  
How JES2 can route output from a series of RJE workstations to one device to either expand or consolidate installation resources.
- “Remote Message Spooling” on page 340.  
How JES2 spools messages that cannot be immediately sent to a remote console.

## Defining RJE Workstations to JES2

RJE workstations are defined to JES2 through the following initialization statements and operator commands. (For detailed information about parameter formats, default values, and other coding considerations, see *z/OS JES2 Initialization and Tuning Reference* and *z/OS JES2 Commands*.)

Table 64. JES2 Initialization Statements and Commands Used to Define a Network

| Statement                    | Purpose                                                                                                                                                                                                                                                                                                                                                                                                        | BSC or SNA |
|------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------|
| APPL(jxxxxxx)                | Associates a JES2 node with a VTAM application identifier and specifies session characteristics for SNA connections.<br><br>See <i>z/OS Communications Server: SNA Resource Definition Reference</i> for information about defining application identifiers.                                                                                                                                                   | SNA        |
| COMPACT                      | Defines a compaction table to be used by JES2 in SNA RJE workstation communications.                                                                                                                                                                                                                                                                                                                           | SNA        |
| DESTID(jxxxxxx)              | Defines the symbolic name for a JES2 route code, which may define a specific RJE workstation.                                                                                                                                                                                                                                                                                                                  | Both       |
| LINE(nnnn)                   | Defines the characteristics of a telecommunication line, such as whether it is a logical SNA line (UNIT=SNA) or an actual BSC line (UNIT= the line's unit address).                                                                                                                                                                                                                                            | Both       |
| LOGON(nnn)                   | Specifies the VTAM application identifier this node uses to communicate with VTAM for a SNA connection.                                                                                                                                                                                                                                                                                                        | SNA        |
| RMT(nnnn)<br>\$ADD RMT(nnnn) | Defines an RJE workstation to JES2.<br><br>For SNA RJE workstations, these definitions must specify DEVTYPE=LUTYPE1. LUTYPE1 indicates that this RJE workstation requires a logical line to communicate with JES2. Also, SNA RJE workstations can specify CONS=YES if the workstation contains a remote console. This remote console is considered as one of the eight devices an RJE workstation can possess. | Both       |

Table 64. JES2 Initialization Statements and Commands Used to Define a Network (continued)

| Statement | Purpose                                                                                                                                                                                                                                                 | BSC or SNA |
|-----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------|
| TPDEF     | Defines the JES2 teleprocessing characteristics: <ul style="list-style-type: none"> <li>• Buffer size and placement</li> <li>• VTAM sessions</li> <li>• Message limits for remote consoles</li> <li>• Highest number RJE workstation allowed</li> </ul> | Both       |

You can define an RJE workstation on one or more members of a multi-access spool (MAS) configuration, but an RJE workstation can be active on only one member at a time. If an RJE workstation is not defined on a particular member, then no device control blocks (DCBs) are allocated for that RJE workstation on that member. The processor control elements (PCEs) required to support the devices attached to RJE workstations are not allocated until the RJE workstation becomes active and are not freed until the RJE workstation is no longer connected. Also, note that necessary control blocks for BSC RJE workstations on dedicated lines are built when the line is started.

An installation must specify a RMT(nnnn) statement or a \$ADD RMT(nnnn) command to define an RJE workstation. Specify the highest number for an RJE workstation allowed on a member through the RMTNUM= parameter on the TPDEF initialization statement. The RMTNUM= parameter defines the virtual storage (68 bytes below 16 Mb in virtual storage for each RJE workstation) for RJE workstations. If RMTNUM=99, JES2 provides enough virtual storage for 99 RJE workstations whether those RJE workstations have been defined or not. If, at initialization, your highest-numbered RJE workstation is numbered above the RMTNUM= value, for example, you define RJE workstation 106, JES2 accepts the definition, increases RMTNUM= to 106, and responds with the following informational message:

```
$HASP510 TPDEF RMTNUM PARAMETER INCREASED TO 106
```

where 106 is the highest numbered RJE workstation specified at initialization. By defining RJE workstation (RMT106) be aware that you have left a 'gap' of six (RMT100 through RMT105) RJE workstations that are available for future definition.

## Planning for RJE Workstation System Growth

Define the RMTNUM= parameter carefully to minimize the amount of unused virtual storage on your JES2 member. However, if you expect to add additional RJE workstations, you should consider setting up your RJE workstation definitions by either:

- Setting this number somewhat higher than your current configuration requires to create a pool of available RJE workstation definitions or
- Leave 'gaps' in your RJE workstation definitions that although specified at initialization are only defined when you need them at some future time. Remember the use of \$ADD RMT is limited by the highest numbered RJE workstation.

If you do not specify the RMTNUM= parameter, it defaults to the highest-numbered RJE workstation specified at initialization. If you do specify RMTNUM=, as noted above, it can be overridden, but **only** during initialization. After initialization, you cannot add an RJE workstation with a number higher than that specified on the



RMTNUM= parameter. If you enter a \$ADD RMT(nnnn) command for an RJE workstation greater than the RMTNUM= parameter value, JES2 responds with an error message.

## Defining RJE Devices

If you specify an RMT(nnnn) statement or a \$ADD RMT(nnnn) command without any parameters, JES2 provides the default of 1 remote printer, 1 remote reader, and 0 remote punches. During initialization, if the NUMPRT= parameter defaults to 1 and an installation defines two remote printers, JES2 recognizes only the first remote printer.

You can specify an RMT(nnnn) statement as follows:

```
RMT(6) NUMPRT=0,NUMPUN=1...
```

to instruct JES2 to provide 1 punch and, by default, 1 reader.

If you specify an RMT(nnnn) statement explicitly defining no devices,

```
RMT(5) NUMPRT=0,NUMPUN=0,NUMRDR=0...
```

the RJE workstation is not defined to the JES2 member. If you enter a \$ADD RMT(nnnn) command or a \$T RMT(nnnn) command explicitly defining no devices, JES2 issues an error message.

**Note:** For SNA RJE workstations, CONS=Yes specifies a console as a device, and this device is counted as 1 of the 8 allowed total devices that can be attached to the RJE workstation (readers are not included in this 8-device limitation). You must define at least one device (printer, punch, reader, or a console) for JES2 to consider the RJE workstation definition to be valid.

After initialization, if you need to add RJE workstations, you can use the \$ADD RMT command to do so if:

- The RJE workstation is numbered less than or equal to the RMTNUM= parameter on the TPDEF statement. (Remember, a number higher than RMTNUM= is not valid.)
- You define RJE workstations with numbers from a pool of numbered but yet undefined RJE workstations. (Because you planned ahead and set RMTNUM= somewhat higher than you needed when you initialized JES2 or left gaps in your RJE workstation definition as noted in “Planning for RJE Workstation System Growth” on page 319.)

Be aware that any RJE workstation added by the \$ADD RMT command is lost across a JES2 restart. Therefore, if you want to permanently retain this remote definition, either when convenient or on the next JES2 restart, add the appropriate RMT(nnnn) initialization statements to your initialization data set.

Although you cannot add remote devices (R(nnnn).PR(m), R(nnnn).PU(m), and R(nnnn).RD(m) ) directly, you can add them by defining them on the RMT(nnnn) NUMPRT=, NUMPUN=, and NUMRDR= parameters. This defines them to JES2 with all their defaults. Once defined here, use the \$T R(nnnn).PR(m), \$T R(nnnn).PU(m), and \$T R(nnnn).RD(m) commands, to reset the default values as you require. For example, at initialization your initialization data set contained:

```
TPDEF RMTNUM=206...
RMT(1)...
:
:
RMT(200)...
```

This provided a pool of RJE workstations numbered 201 through 206 for future use. You can now enter, for example:

```
$ADD RMT(201-206) NUMPRT=4,NUMRDR=2...
```

This command adds 4 printers and 2 readers to each of the 6 new RJE workstations (RMT201 through RMT206). Then use the \$T R20n.PRm and \$T R20n.RDm commands to select printer and reader specifications appropriate to your installation. Such as:

```
$tr201.pr1,cl=a,forms=letter...
$tr201.pr2,cl=b,forms=legal...
:
$tr206.pr4...
```

Conversely, when you need to decrease the number of remote devices, do so by decreasing the NUMPRT=, NUMPUN=, or NUMRDR= values. JES2 deletes the devices in descending order starting with the highest numbered device (of the specified type) first. Continuing with the previous example that added four printers to RMT(206), issuing

```
$T RMT(206) NUMPRT=2
```

causes JES2 to delete the two highest-numbered printers (PR4 and PR3) on RMT(206).

## Modifying RJE Workstations

Some parameters on the RMT(nnnn) definition can be modified regardless of whether the RJE workstation is active or not. Most parameters, however, can be modified through a \$T RMT(nnnn) command only if the RJE workstation is not active. You can determine whether an RJE workstation is active or inactive by either:

- Entering the \$D RMT(nnnn) command - the STATUS= value displays as ACTIVE or INACTIVE.
- Entering the \$D ACTRMT(nnnn) command - \$HASP137 displays all the active RJE workstations throughout the MAS, on a particular member, or a particular workstation on a particular member (based on how you use the command's filtering capabilities).

### Notes:

1. If you modify an RJE workstation using the \$T command, for most parameters the RJE workstation need only be inactive on the member on which you are changing the definition. If a response from a \$D ACTRMT command shows the RJE workstation as active on some other member, all RMT parameter definitions can still be modified.
2. If you enter a \$T RMT(nnnn) command that includes one of the parameters that requires that the RJE workstation be inactive against an active RJE workstation, JES2 responds with an error message.

## Recovering RJE Workstations from Failed Members

If a member of your MAS fails while an RJE workstation was active, the RJE workstation can sign on to another member of the MAS.

Because JES2 automatically resets the record of active RJE workstations when a member fails, you can activate an RJE workstation on a member if:

- It is not active elsewhere in the MAS, and

- At least one member of the JES2 MAS is active or made active at JES2 SP5.2 or later prior to reactivating the failed member (and its remote workstations).

If a member fails and no other MAS member (at SP5.2 or higher) is active, those RJE workstations active at the time the JES2 member failed cannot be restarted until the failing member is restarted.

To determine the active RJE workstations in a MAS, enter the \$D ACTRMT(nnnn) command. JES2 responds with the following console display:

```
$HASP137 ACTRMT(nnnn) MEMBER=memname
```

where *nnnn* specifies the number of the active RJE workstation and *memname* indicates the name of the member (derived from the MEMBER(nn) initialization statement) on which this RJE workstation is active.

---

## SNA RJE Considerations

Remote job entry workstations use systems network architecture (SNA) to gain access to JES2 through VTAM. During VTAM system definition, these RJE workstations (for example, 3790 terminals, 3770 terminals, and System/32 workstations) are defined to VTAM as logical units (LUs) and physical units (PUs) by means of the VTAM LU and PU definition statements, respectively. At VTAM system definition, each installation must decide how to tailor the JES2/VTAM support for its SNA stations. The parameters of the LU and PU statements affect not only how JES2 operates, but also how the remote operator uses the workstation.

## VTAM LU and PU Parameters that Affect SNA RJE

Some of the LU parameters affect both the logon syntax and the handling of logon requests. For a description of what the following parameters specify and how to code the LU macro instruction, refer to *z/OS Communications Server: SNA Resource Definition Reference*. The teleprocessing links (the physical connections) are transparent to JES2; they are managed exclusively by VTAM and the network control program (NCP).

The following LU parameters are a small subset of those that affect the VTAM session with JES2:

*Table 65. VTAM Parameters that Affect JES2*

| Unit Type | Name   | Purpose                                                                                  |
|-----------|--------|------------------------------------------------------------------------------------------|
| LU        | USSTAB | Specifies a table to be used in generating a logon sequence.                             |
| LU        | SSCPFM | Specifies whether an RJE workstation supports formatted or unformatted systems services. |
| PU        | DISCNT | Specifies how the teleprocessing link is to be disconnected.                             |

## VTAM APPL Definitions for SNA RJE

A VTAM APPL definition statement defines an application program to VTAM. JES2 requires the following values from the VTAM APPL statement:

Table 66. VTAM APPL Statement Parameters Necessary for a JES2 Connection

| Parameter | Purpose                                                                                                                                                       |
|-----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| AUTH=ACQ  | Specifies the setting (ACQ) if this RJE workstation uses automatic logon.                                                                                     |
| APPLNAME= | Corresponds to the APPLID= parameter on the JES2 LOGON(nnn) initialization statement. (The LOGON(2) is used as the default APPLID for JES2 initiated logons.) |
| PRCT=     | Corresponds to the PASSWORD= parameter on the JES2 LOGON(nnn) initialization statement.                                                                       |

## SNA RJE Buffer Size

Each teleprocessing buffer for SNA is prefixed in storage with a request parameter list (RPL). JES2 uses the values you have specified to determine the buffer size for RJE processing. JES2:

1. Starts with the SNABUF=(SIZE= ) parameter value (within a range of 256-3840) on the TPDEF initialization statement.
2. Increase SIZE= value to BUFSIZE= parameter value on the SNA RMT(nnnn) initialization statement if BUFSIZE= is larger than SIZE=.
3. Increase SIZE= to 280 bytes if SIZE= is less than 280, and the LINENUM= parameter on the NJEDEF initialization statement is greater than 0.
4. Adds 256 (the size of the RPL prefix) to the buffer size, rounded up to a multiple of 8, and rounded down to a maximum of 4096.

You can calculate the 'usable' teleprocessing (TP) buffer size by subtracting the RPL prefix area. You can display this value with a \$D TPDEF operator command, which results in the \$HASP839 message.

### Valid RU Sizes

The actual transmission response/request unit (RU) size for SNA RJE buffer is limited further (rounded down) by the SNA Architecture, and JES2 enforces the restriction through the BUFSIZE= parameter on the RMT(nnnn) definition.

After initialization, if you use the \$ADD RMT(nnnn) command to add a SNA RJE workstation, or you use the \$T RMT(nnnn) command to modify one, the BUFSIZE= parameter value cannot be larger than the SNABUF=(SIZE=) parameter value on the TPDEF initialization statement. The BUFSIZE= parameter is rounded down for RU bind limitations before it is checked against the SNABUF=(SIZE=) parameter value on the TPDEF initialization statement.

---

## BSC RJE Processing

Reading, printing, and punching between the host processor and the RJE workstation are asynchronous events. For example, the processor is either transmitting print data or transmitting punch data or reading an input stream. For an explanation of how the remote operator can influence the order of these events, see "Altering the Sequence of Operations from an RJE Workstation" on page 337.

Communication between the local processor and BSC RJE workstations uses a JES2 facility, called **multileaving**, which simulates the transmission of multiple print and punch streams. Multileaving allows JES2 to receive multiple console messages and input streams. With multileaving, several operations can take place simultaneously. Operators at RJE workstations that have no console can enter

commands into the input stream in the normal manner. Command replies are scheduled back to the RJE workstation for printing on a remote printer.

RMT generation is the JES2 procedure for generating multileaving remote terminal processor programs for RJE from programmable RJE workstations. An RJE workstation is established by a JES2 program, RMTGEN, during or after system installation. These programs allow multileaving workstations (see “BSC Multileaving Workstations Supported by JES2”) to operate as RJE workstations with JES2. RMT generation requires other procedures for its processing; for example, procedures for allocating space and cataloging. It also requires certain spool data sets for job processing after generation. These procedures and data sets, also required by JES2 generation, are described in “Part 2. Controlling JES2 Processes” on page 69.

## BSC Multileaving Workstations Supported by JES2

JES2 provides RJE workstations with multileaving support for the following programmable workstations:

- IBM System/360\* Model 20 (Submodels 2, 4, 5, and 6) and the 2922 Remote Workstation RTP program with the following selectable options:
  - 1403 Printer
  - 1442 Card Read Punch
  - 2152 Printer-KeyBoard
  - 2203 Printer
  - 2501 Card Reader
  - 2520 Card Read Punch
  - 2560 Multi-Function Card Machine
- IBM System/360 (Models 22 and up) and System/370 (Models 115, 125, 135, 145, 148, 155, 158, 165, 168, and 195) with the following selectable options:
  - 1052 Printer-KeyBoard
  - 1403 Printer
  - 1442 Card Read Punch
  - 1443 Printer
  - 2501 Card Reader
  - 2520 Card Read Punch
  - 2540 Card Read Punch
  - 3203 Printer (supports 3203-1 through 3203-4)
  - 3210/3215 Printer-KeyBoard (supported as a 1052)
  - 3211 Printer
  - 3504 Card Reader (supported as a 2501)
  - 3505 Card Reader (supported as a 2501)
  - 3525 Card Punch (supported as a 1442)
  - 5203 Printer
  - 5313 Console for the Model 125 (requires 1052 compatibility feature)

## BSC Teleprocessing Buffer Considerations

The BSCBUF=(SIZE=) parameter on the TPDEF initialization statement specifies the size of BSC teleprocessing buffers that JES2 allocates below 16 megabytes in virtual storage. This value is specified in bytes (520-3960). If you do not specify this parameter during initialization, JES2 provides the minimum of 520 bytes.

After initialization, if you use the \$ADD RMT(nnnn) command to add a BSC RJE workstation, or you use the \$T RMT(nnnn) command to modify one, the BUFSIZE=

parameter value cannot be larger than the BSCBUF=(SIZE=) parameter value on the TPDEF initialization statement. If you specify a larger BUFSIZE value, JES2 responds with an error message.

If you specify the following values for the TPDEF initialization statement, the SIZE= subparameters on BSCBUF= can be overridden.

```
TPDEF SNABUF=(LIMIT=200,SIZE=1840),
 BSCBUF=(LIMIT=200,SIZE=1792),
 MBUFSIZE=1840
```

After initialization, a \$D TPDEF command would display the following:

```
$HASP839 AUTOINTV=32,BSCBUF=(LIMIT=200,WARN=90,SIZE=1840)
$HASP839 MBUFSIZE=1840,RMTMSG=150,RMTNUM=50,SESSION=65535,
$HASP839 SNABUF=(LIMIT=200,WARN=80,SIZE=1840)
```

To avoid having the SIZE= subparameters for BSCBUF= overwritten by the MBUFSIZE= parameter, ensure that the value of the SIZE= subparameter is greater than that specified by MBUFSIZE=.

**Note:** If a RMT(nnnn) initialization statement specifies a higher BUFSIZE= value, JES2 increases the BSCBUF=(SIZE=) parameter.

---

## SMF Record Summary: RJE Processing

The following lists the SMF records written during RJE processing. For a complete list of the record contents, see *z/OS MVS System Management Facilities (SMF)*.

Table 67. SMF Records Used by JES2 RJE

| Record Number | Action that Causes the Record to be Written                                                                                                                                                                |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 47            | <ul style="list-style-type: none"><li>• A BSC line is started [\$S LINE(n) command].</li><li>• A BSC line is restarted [\$E LINE(n) command].</li><li>• A BSC RJE workstation user signs on.</li></ul>     |
| 48            | <ul style="list-style-type: none"><li>• A BSC line is stopped [\$P LINE(n) command].</li><li>• A BSC line is restarted [\$E LINE(n) command].</li><li>• A BSC RJE workstation user signs off.</li></ul>    |
| 49            | A BSC RJE workstation user signs on with an incorrect password.                                                                                                                                            |
| 52            | <ul style="list-style-type: none"><li>• An SNA line is started [\$S LINE(n) command].</li><li>• An SNA line is restarted [\$E LINE(n) command].</li><li>• An SNA RJE workstation user signs on.</li></ul>  |
| 53            | <ul style="list-style-type: none"><li>• An SNA line is stopped [\$P LINE(n) command].</li><li>• An SNA line is restarted [\$E LINE(n) command].</li><li>• An SNA RJE workstation user signs off.</li></ul> |
| 54            | An SNA RJE workstation user signs on with an incorrect password.                                                                                                                                           |

---

## Defining Lines for RJE Workstations

The following explains how to define RJE lines for both BSC and SNA protocols. Define lines that connect remote devices to RJE workstations at initialization on LINE(nnnn) initialization statements. Note the following restrictions:

- You cannot use a line for network job entry (NJE) or have NJE devices dedicated to it.

- You cannot add (through the \$ADD RMTnnnn command) or modify (through the \$T RMTnnnn command) an RJE workstation unless the lines intended for its use have been predefined during initialization.
- You cannot use channel-to-channel (CTC) lines for RJE workstations.

There are two ways an RJE workstation can specify lines during initialization:

- Nondedicated
- Dedicated (often referred to as a **leased line**)

## Nondedicated Lines

A nondedicated line is a line that has been defined, but is not specified on the LINE= parameter of a RMT(nnnn) statement, a \$T RMT(nnnn) command, or a \$ADD RMT(nnnn) command.

To begin an RJE processing session with nondedicated lines, each RJE workstation must provide a /\*SIGNON JES2 control statement. The central operator, who controls BSC line activation for all RJE workstations connected to a member, is aware of workstation use through the /\*SIGNON and /\*SIGNOFF JES2 control statements entered through the console.

For both SNA and BSC RJE workstations, nondedicated RJE workstations can be configured to meet the needs of your installation. For example, one physically connected RJE workstation can be initialized as multiple nondedicated RJE workstations for use by different groups at different times.

When the RJE workstation is not signed on, it cannot process jobs, output, messages, or queue commands to JES2. Although you can queue work to such an RJE workstation, it remains on the JES2 spool until the RJE workstation again signs on. Also, one RJE workstation can be used as a backup for an inoperable RJE workstation. You must sign-on the backup RJE workstation with the inoperable RJE workstation's ID.

### RJE BSC Dial-Up Connections

RJE workstations that require the operator to dial a number to connect them to the JES2 processor (through **dial-up** lines) normally do not specify a dedicated line. Therefore these dial-up RJE workstations can connect to any available nondedicated line.

However, RJE workstations connected through dial-up lines might be considered a data security risk at your installation. Because the line remains active, the RJE workstation operator must not disconnect the line before signing off the RJE processing session.

Any RJE workstation can lease nondedicated lines through either the \$T RMT(nnnn) command or the \$ADD RMT(nnnn) command causing the line to become dedicated.

## Dedicated Lines

A dedicated line is defined and specified on the LINE= parameter of a RMT(nnnn) statement, a \$T RMT(nnnn) command, or a \$ADD RMT(nnnn) command.

An installation can configure dedicated lines and RJE workstations that must be connected by dial-up facilities; however, typically, dial-up RJE workstations do not use dedicated lines.



Dedicated lines can be **shared** if two or more RMT(nnnn) initialization statements specify the same line on the LINE= parameter. However, only one RJE workstation can sign-on to the line at a time. To begin an RJE processing session with shared lines, each RJE workstation must provide a /\*SIGNON JES2 control statement or VTAM LOGON.

---

## Defining BSC Lines for RJE Workstations

JES2 allocates resources for BSC lines only when the lines are active. These resources can include a substantial amount of storage that is required by the processor control elements (PCEs) to support devices attached to RJE workstations.

A BSC dedicated line is **non-shared** if the SHARABLE=NO parameter is specified on the RMT(nnnn) initialization statement. However, setting SHARABLE=YES defines the line as capable of being shared; not that it is being shared, and once specified as SHARABLE=YES, the line will require sign on. If you enter a \$D LINE command, a non-shared line displays RMTSHARE=NO and does not require sign on.

Dedicated lines that are non-shared do not require a /\*SIGNON JES2 control statement to begin an RJE processing session. If you specify a /\*SIGNON statement on a dedicated line, it is ignored because the workstation is considered active when the line is started. Note that lines are started by the central operator, who might not be aware of station use. Because specifying a /\*SIGNON statement is a manual process at all RJE workstations, dedicating lines as non-shared conserves resources.

BSC lines that have been defined as dedicated can be **sharable** by specifying SHARABLE=YES on the RMT(nnnn) initialization statement, \$T RMT(nnnn) command, or a \$ADD RMT(nnnn) command. You can choose this option if you want to restrict particular lines to particular RJE workstations, but want the security provided by a /\*SIGNON JES2 control statement.

Consider the following RJE workstation and line definitions to illustrate how RJE workstations can be defined as sharable or non-sharable, your use of a /\*SIGNON statement, and how JES2 deals with conflicting shared line definitions:

### Example 1

```
LINE(3) UNIT=3099,...
:
RMT(16) LINE=3,SHARABLE=YES,...
```

Example 1 defines LINE3 and a single RJE workstation (RMT16) that will use that line. However, SHARABLE=YES indicates that if another RJE workstation also defines LINE3 it can do so. In any case, a /\*SIGNON JES2 control statement is required.

### Example 2

```
 LINE(27) UNIT=2799,...
 :
 RMT(17) LINE=27,SHARABLE=YES,...
 RMT(18) LINE=27,SHARABLE=YES,...
```

Example 2 defines LINE27 and two RJE workstations (RMT17 and RMT18) that will use that line. However, if you mistakenly defined RMT17 by specifying SHARABLE=NO (with the intention of wanting it to share the line with RMT18), JES2 forces the RMT17 definition to SHARABLE=YES and you still obtain the desired result. Therefore, if two RMT(nnnn) statements specify the same line, the line is shared. To warn you of such an error, JES2 issues \$HASP456 LINEnnnn REQUEST TO BE NON-SHARED BY REMOTE DENIED.

Now consider Example 3:

### Example 3

```
 LINE(27) UNIT=2799,...
 :
 RMT(17) LINE=27,SHARABLE=YES,...
 RMT(18) LINE=0,SHARABLE=YES,...
```

Although both RMT17 and RMT18 are defined as SHARABLE=YES, the RMT18 definition now specifies LINE=0 rather than LINE=27 as it did in Example 2. JES2 defines RMT18 as capable of using any **nondedicated** BSC line. A /\*SIGNON JCL statement is required to start the RJE workstation. Although LINE27 is no longer shared, JES2 will indicate RMTSHARE=YES in response to a \$D RMT17 command.

### Example 4

```
 LINE(27) UNIT=2799,...
 :
 RMT(16) LINE=3,SHARABLE=YES,...
 RMT(17) LINE=27,SHARABLE=NO,...
 RMT(18) LINE=27,SHARABLE=NO,...
```

If however, you intended each RJE workstation (RMT17 and RMT18) to use a different line and mistakenly defined each to the same line (as shown in Example 4), JES2 forces both definitions to SHARABLE=YES and both RJE workstations use LINE27, different from your expectations and likely having availability implications. As in Example 2, JES2 issues \$HASP456 LINEnnnn REQUEST TO BE NON-SHARED BY REMOTE DENIED to warn you of such an error.

---

## Defining SNA Lines for RJE Workstations

When using SNA protocols for RJE, note that all RJE workstations (except those defined as AUTOLOG=YES) specify a LOGON initialization statement to begin an RJE processing session. SNA workstations never use the /\*SIGNON JES2 control statement. SNA workstations end a session through the VTAM LOGOFF command.

### RJE Line Passwords

An installation can establish a relationship between RJE workstations and lines through line passwords. A line password, defined by the PASSWORD= parameter on the LINE(nnnn) initialization statement, guarantees either a user or a group of users the use of a particular line and prevents unauthorized RJE workstation operators from using that line to gain access to JES2.

To increase security checking, in addition to standard password processing, your installation can use JES2 Exit 17 for BSC RJE sign-on and sign-off and Exit 18 for SNA RJE logon and logoff. See *z/OS JES2 Installation Exits* for more information.

### Changing an RJE Workstation from BSC to SNA

While your JES2 member is active, you might want to upgrade your installation's processor by changing an RJE workstation from BSC to SNA for RJE processing. To accomplish this task, perform the following steps on an inactive RJE workstation:

1. Set the LINE= parameter on your RMT(nnnn) initialization statement to zero through a \$T RMT(nnnn) command:  
`$T RMT4,LINE=0`
2. Redefine the predefined teleprocessing line as a logical line:  
`$T LINE11,UNIT=SNA`
3. Redefine the terminal type to indicate that it is a logical terminal that can be accessed only through a logical line.  
`$T RMT4,DEVTYPE=LUTYPE1,LINE=11`

Review all other RJE workstation parameters (such as BUFSIZE= ) to ensure they are appropriate for a SNA RJE workstation.

### Changing an RJE Workstation from SNA to BSC

You might choose to change a SNA remote workstation to a BSC RJE workstation. Perform the following steps to change an inactive RJE workstation from using a SNA line to using a dedicated BSC line:

1. Modify the LINE= parameter on the RMT(nnnn) initialization statement through a \$T RMT(nnnn) command:  
`$T RMT4,LINE=0`
2. Redefine the predefined logical line:  
`$T LINE4,UNIT=30A`
3. Redefine the terminal type to indicate the type of terminal or processor (multileaving or hardware) being used at this RJE workstation location.  
`$T RMT4,DEVTYPE=2770,LINE=4`

Review all other RJE workstation parameters (such as BUFSIZE= ) to ensure that they are appropriate for a BSC RJE workstation.

---

## Using Compaction on SNA RJE Workstations

Compaction, which is available only for SNA RJE workstations, is used to increase data transmission efficiency by compacting master character pairs into a single 8-bit representation (4 bits per character).

Data transmissions to RJE workstations and remote devices can be compacted if compaction is specified. The COMPACT initialization statement defines the characters to be compacted (master characters) and the characters to be recognized by the compaction routines but not compacted (nonmaster characters).

In the example below, the compaction table NEWONES specifies 15 master characters (the numbers 0-9 and the vowels A, E, I, O, and U) and 16 nonmaster characters. The NUMBER= parameter specifies a number by which both the installation and JES2 can refer to this table. If you do not specify a table name, NAME= defaults to the NUMBER= parameter value. You must specify the NUMBER= parameter.

```
COMPACT NAME=NEWONES,CHARS=(15,0,1,2,3,4,5,6,7,8,9,A,E,I,O,U,
40,B,C,D,F,G,H,J,K,L,M,N,61,$,T,S),NUMBER=1
```

The COMPACT=YES parameter specification on the RMT(nnnn) statement, the \$ADD RMT(nnnn) command, or the \$T RMT(nnnn) operator command allows you to specify if an RJE workstation is to accept compacted data. The COMPACT parameter on the R(nnnn).PR(m) and R(nnnn).PU(m) statements is set equal to a valid compaction table identifier (which is specified on the COMPACT initialization statement) if compaction is desired for the remote device. Also, the device must specify CMPCT=YES or JES2 does not compact the data.

The /\*OUTPUT JES2 control statement or the JCL OUTPUT statement can be used to override the R(nnnn).PR(m) and R(nnnn).PU(m) statements. However, neither the /\*OUTPUT statement nor the JCL OUTPUT statement has any effect on compaction for node-to-node transmissions (SNA NJE) because such compaction is done on a session basis. For further information, see *z/OS MVS JCL Reference*.

## How Compaction Works

In the compaction algorithm, 3 to 16 user-specified master characters are assigned 4-bit representations to replace their conventional EBCDIC values. When master characters occur in pairs, in any combination, each pair can be compacted and represented by a single 8-bit value.

Because compaction allows the assignment of 3 to 16 master characters, as many as 244 nonmaster characters can be assigned. Nonmaster characters are not compacted, but when they occur in pairs with master characters or singly they do not require breaking the compaction string. When characters other than master or nonmaster are encountered, the compaction string is broken and the characters are transmitted in their standard representation.

To determine the best set of master and nonmaster characters, you must examine the nature of your installation's transmitted data. For example, if most data is numeric, you could compact the characters 0-9, +, -,., and =. You would still have 46 nonmaster characters in which to specify other frequently used special characters and alphabets.

When establishing a set of master characters for compaction, remember that master characters are not compacted singly, but in various combinations of pairs.

---

## Starting and Stopping Remote Job Entry

Because teleprocessing lines are never considered active at JES2 initialization, each line must be activated using a JES2 start command (\$S). An RJE workstation cannot be started on a member if it is already active on another member of the MAS. Use the \$D ACTRMT(nnnn) command to determine the remote's status before you attempt to start it. The \$S command can be issued by the operator through a command stream (for example, through the JES2 initialization data set), entered into a job stream, or through the automatic command processor. A line is dynamically allocated when activated. A line can be deactivated and deallocated using the JES2 stop command (\$P).

A remote device is considered active when its RJE workstation becomes active, provided that the device is specified for automatic start by the START= parameter on the following initialization statements:

- R(nnnn).RD(m)
- R(nnnn).PR(m)
- R(nnnn).PU(m)

Otherwise, the device is considered inactive and must be started either by the RJE workstation or through local operator command.

## Options for Disconnecting Remote Lines

To minimize data security problems when using BSC dial-up lines, always specify AUTODISC=YES on the LINE(nnnn) statement for each dial-up line. When you specify AUTODISC=YES, JES2 disconnects a line automatically by simulating a \$E command sequence when it detects a not-ready data set condition. (The circumstances in which JES2 detects a not-ready data set condition depends on different factors, including line configuration.)

If you specify AUTODISC=NO or do not specify this parameter during initialization, the line remains active; JES2 waits for either the data set to be made ready or the operator to take action.

Ensure that remote operators sign off prior to disconnecting a line. If a line-drop or a disconnect occurs on a dial-up line prior to sign off, another user might connect to the same port and receive data intended for the prior user of that port. (To ensure the transmission of data to the proper authorized remote terminals, use SNA or dedicated lines.)

For both SNA and BSC RJE workstations, you can also cause JES2 to automatically disconnect an inactive RJE workstation by coding a nonzero value for the DISCINTV= parameter on the RMT(nnnn) statement at JES2 initialization, the \$ADD RMT(nnnn) command, or the \$T RMT(nnnn) command while the member is inactive. When the amount of time specified in the DISCINTV= parameter elapses with no data sent or received on the line, JES2 disconnects the line by simulating a \$E command sequence.

## BSC Workstations

The first action taken at nondedicated or dedicated and shareable RJE workstation is the submission of a sign-on statement. This statement must be submitted through the input stream as a single-image statement, and cannot be immediately followed by the first job. (Sign-on is ignored for dedicated, non-shared lines.)

When an RJE workstation signon is successfully completed, JES2 sends a message to the RJE workstation verifying the successful signon.

## Format and Definitions for the /\*SIGNON Statement

| Column | Description        |
|--------|--------------------|
| 1      | /*SIGNON           |
| 16     | REMOTEnn   RMTnnnn |
| 25     | password1          |
| 35     | newpass            |
| 73     | password2          |

### RMTnnnn|REMOTEnn

Defines the RJE workstation requesting sign-on.

**Note:** The long form (REMOTEnn) is only valid for RJE workstations 1 through 99.

### password1

Defines the password established at initialization or changed by the operator for that line. If the line has a password, then password1 is required.

To establish password1, specify the LINE(nnnn) JES2 initialization statement. You can change this password through the \$T LINE(nnnn) command.

### newpass

Specifies the password used by the Resource Access Control Facility (RACF) to change the password of this remote. If RACF is not active, you cannot change the remote's password in this way. See "Part 7. Providing Security for JES2" on page 341 for information about using RACF to control RJE workstations.

If you are using RACF to control the RJE workstations, you must specify newpass the first time this remote issues a logon or signon. Otherwise, RACF will reject the access attempt. See "Part 7. Providing Security for JES2" on page 341 for information about defining an RJE workstation to RACF.

### Password2

Defines the password maintained by RACF unless you use JES2 remote password control. If you use JES2 remote password control, JES2 establishes this password through a RMT(nnnn) initialization statement, or through a \$ADD RMT(nnnn) command or a \$T RMT(nnnn) command.

If the terminal has a password, then password2 is required to ensure that the RJE workstation signing on is a valid workstation.

## Format for the /\*SIGNOFF Statement

A sign-off statement is submitted to end BSC job stream processing. This statement, too, should be submitted through a card reader as a single-image statement, as is the /\*SIGNON statement.

| Column | Description |
|--------|-------------|
| 1      | /*SIGNOFF   |

## SNA RJE Workstations

There are three ways that the operator can initiate an automatic terminal connection:

1. Entering the VTAM LOGON command that identifies the VTAM application ID to JES2.

2. Specifying AUTOLOG=YES on the RMT(nnnn) definition to make the RJE workstation eligible for automatic logon whenever work exists.  
This parameter causes JES2 to connect to an RJE workstation when SYSOUT is queued for processing.
3. Entering the \$\$ RMT(nnnn) command to force a connection whether or not any work exists.  
This command starts the JES2/VTAM interface, which allows JES2 to begin processing logons from the RJE workstations and terminals through the following command:  
\$\$ LGN(2)

If you use either method 2 or 3, you must also specify the logical unit name (LUNAME=) on the RMT(nnnn) statement, \$ADD RMT(nnnn) command, or \$T RMT(nnnn) command.

### Initiating an Automatic Terminal Connection

The operator can issue an automatic logon command before the JES2/VTAM interface is started. However, JES2 does not act upon the automatic logon command until the operator starts the logical lines and the JES2/VTAM interface. If, however, the RJE workstation is a multi-logical unit (MLU) device, JES2 automatically initiates one session only when AUTOLOG=YES

**JES2 Automatic Logon Capability:** The automatic logon capability allows JES2 to contact and connect an RJE terminal automatically. This can occur either when output (print/punch) or messages are queued for transmission for that terminal or when an authorized console operator issues the appropriate JES2 command. Automatic logon allows maximum use of communication facilities such as lines, adapters, modems, and controllers. For example, a line can be dedicated to a terminal using automatic logon. The efficiency is increased because RJE workstations need not remain logged on while waiting for output. This frees facilities for use with other terminals and applications.

Although JES2 automatically calls (actually dials-out in some cases) an RJE workstation to produce output or messages, the need for a terminal operator is still present. *Automatic logon does not provide for unattended operation of the terminal.* The operator must continue to control the terminal and take the necessary error recovery actions.

The automatic logon capability is available only to terminals operating in a VTAM network using SDLC (synchronous data link control) or RECORD-mode communications. *BSC RJE workstations are not supported by automatic logon.*

**Making the RJE Workstation Eligible When Work Exists:** Specifying AUTOLOG=YES causes JES2 to check the output queues periodically for work. The RJE workstation will be eligible for automatic connection whenever work exists.

The RJE workstation cannot connect immediately if there is a resource shortage. However, the member retries the connection request until it is successful or until a permanent error is recorded. The RJE workstation will remain connected until it has been signed off by its operator. If an appropriate disconnect interval has been specified (the DISCINTV= statement of the RMT(nnnn) initialization statement), the RJE workstation will be disconnected automatically when it becomes idle.

**Making the RJE Workstation Eligible Whether or Not Work Exists:** An authorized (system authorization) operator can force a remote terminal to be eligible for connection regardless of whether or not work is queued for it by issuing a \$\$



RMT(nnnn) command. The RJE workstation cannot connect immediately if there is a resource shortage. However, the member retries the connection request until it is successful or until a permanent error is recorded.

**Automatic Logon Considerations:** To initialize the automatic logon capability for use with SNA LUTYPE1 terminals, the RMT(nnnn) statement, \$ADD RMT(nnnn) command, or \$T RMT(nnnn) command for the RJE workstation must specify the name of the VTAM logical unit (LU) to be contacted through the LUNAME= operand. Because the automatic logon is performed internally, JES2 does not receive any logon message or password data. Therefore, an RJE workstation connected by automatic logon never uses a communication line that has been assigned a line password. Sufficient lines (without line passwords) should be initialized through the LINE(nnnn) initialization statement to allow for expected automatic logon activity.

For normal logon procedures, the \$S LGN(n) command should be issued after VTAM has been started. (When VTAM has been started, both the network controllers or communication links needed to establish a path to the remote station and the physical unit and logical unit associated with the station must be activated.) To allow an SNA RJE workstation to log on, the operator must also issue \$S LNE(n) to activate a line to VTAM for the SNA RJE workstation.

### Creating a SNA RJE Connection

JES2 attempts to contact a terminal only when there are sufficient resources to allow connection. To establish a session, certain conditions must be met. If any of these conditions are not met, the RJE workstation is not logged on immediately. The member retries the automatic logon attempt periodically until it is successful. If the RJE workstation is currently in contact with another application (prevents logon), the connection request will be retried periodically.

- The RJE workstation must not be already connected to the system.
- A JES2/VTAM application interface must be available (logon DCT started).
- The RJE workstation must not be connected to another processor in the same MAS configuration.
- A JES2 logical line that does not have a line password defined must be available (started and not in use by any other RJE workstation).
- The system must not have reached the session limit specified by the SESSION= parameter on the TPDEF initialization statement.
- Enough storage must be available for the processor control elements (PCEs) required to support the devices attached to the RJE workstations. This storage requirement can be substantial depending upon the device configuration.

### Using the VTAM LOGON Command for SNA RJE

The SNA RJE workstations use the LOGON command to request a session with JES2. When the operator issues the LOGON command, VTAM notifies JES2 that a logon has been received, and passes to JES2 the data sent with the LOGON command. If the data is acceptable, JES2 establishes a session with the logical unit (LU) associated with the RJE workstation.

The syntax of the LOGON command for each LU is established at JES2 and VTAM system definition. For example, the password included in the data sent with LOGON might or might not be required; the operator must be told what syntax to use.

The default VTAM syntax:

```
LOGON APPLID (JES2) [LOGMODE(name)]
DATA (RMTnnnn,password1,password2,newpassword2)
```

## **JES2**

Identifies JES2 as an application program.

## **LOGMODE(name)**

Indicates a mode table entry that JES2 uses to determine some of the characteristics of the session with a SNA terminal. If LOGMODE is not specified, VTAM selects a default bind image. See “JES2 RJE Bind Image” on page 336 for the statements that alter the JES2 bind image.

## **DATA**

Specifies the RJE workstation and any valid passwords.

## **RMTnnnn|REMOTEnn|RMnnnn|Rnnnn|NnnRnnnn**

Specifies the RJE workstation.

**Note:** The long form (REMOTEnn) is only valid for RJE workstations 1 through 99.

## **password1**

Authorizes the use of the SNA line associated with it.

## **password2**

Authorizes the use of the SNA RJE workstation associated with it.

## **newpassword2**

If using RACF, provides a new *password2* for the RJE workstation.

## **Using the VTAM LOGOFF Command for SNA RJE**

SNA RJE workstations can use the JES2 SIGNOFF statement or the VTAM LOGOFF (\$P LGN(n) is used to stop the JES2/VTAM interface). The VTAM LOGOFF command, however, has an option which is not provided by the JES2 SIGNOFF statement. As with the LOGON command, the installation defines the syntax of LOGOFF at VTAM system definition time. The default syntax is:

```
LOGOFF TYPE({COND | UNCOND})
```

## **TYPE**

Indicates whether a conditional or unconditional logoff is requested.

## **CONDIUNCOND**

Indicates that the session will be disconnected at the end of any current data transmission (COND) or immediately, regardless of the data transmission (UNCOND).

For more information about LOGON and LOGOFF, refer to *z/OS Communications Server: SNA Resource Definition Reference*. For a description of \$\$ LGN(n), \$P LGN(n), and \$S LNE(n), refer to *z/OS JES2 Commands*.

---

## JES2 RJE Bind Image

JES2 uses a standard bind image for communication with remote devices. You can only alter this bind image with the VTAM statements listed in Table 68 when JES2 sends the bind image to a remote device.

*Table 68. Variable Statements Used to Alter the JES2 RJE Bind Image*

| <b>Statement</b>                                                             | <b>Source of Value</b>                                                                                                                                                                                                                                                                                                                                                                                                    |
|------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Compression*                                                                 | Can be set on by the user's input bind image. This value defaults to the PRIPROT parameter specified in the user's input bind image.<br><br>Can be set on by the COMPRESS=YES parameter in the RMT(nnnn) initialization statement, the \$ADD RMT(nnnn) command, the \$T RMT(nnnn) command, or the LINE(nnnn) initialization statement.<br><br>Will be reset if alternate code is specified in the user's input bind area. |
| Alternate Code*                                                              | Can be set on by the user's input bind image COMPROT byte 5 bit 4.                                                                                                                                                                                                                                                                                                                                                        |
| Pacing Count                                                                 | Can be set to value of 0 or 1 by the user's input bind image SSNDPAC, byte 7.                                                                                                                                                                                                                                                                                                                                             |
| SLU Send*                                                                    | Can be set to a value (0 to 3F) by the user's input bind image SRCVPAC, byte 8.                                                                                                                                                                                                                                                                                                                                           |
| Pacing Count                                                                 | Will be set by the BUFSIZE= parameter on the RMT(nnnn) initialization statement, the \$ADD Rmt(nnnn) command, or the \$T RMT(nnnn) command.                                                                                                                                                                                                                                                                               |
| SLU Receive*                                                                 |                                                                                                                                                                                                                                                                                                                                                                                                                           |
| RU                                                                           |                                                                                                                                                                                                                                                                                                                                                                                                                           |
| C                                                                            | Can be set on by the COMPACT parameter on the RMT(nnnn) initialization statement, the \$ADD Rmt(nnnn) command, or the \$T RMT(nnnn) command.                                                                                                                                                                                                                                                                              |
| Media Flag                                                                   | Can be set on by the SELECT parameter on the Rnn.PRm and Rnn.PUm R(nnnn).PU(m) initialization statements, or the \$T R(nnnn).PR(m) and \$T R(nnnn).PU(m) operator commands.                                                                                                                                                                                                                                               |
| PDIR                                                                         | Can be set on by the SETUP= parameter on the RMT(nnnn) initialization statement, the \$ADD Rmt(nnnn) command, or the \$T RMT(nnnn) command.                                                                                                                                                                                                                                                                               |
| PDIR Flag                                                                    | Can be set on by the SETUP= parameter on the RMT(nnnn) initialization statement, the \$ADD Rmt(nnnn) command, or the \$T RMT(nnnn) command.                                                                                                                                                                                                                                                                               |
| Media                                                                        | Can be set on by the SELECT= parameter on the R(nnnn).PR(m) and R(nnnn).PU(m) initialization statements, or the \$T R(nnnn).PR(m) and \$T R(nnnn).PU(m) operator commands.                                                                                                                                                                                                                                                |
| Presentation                                                                 | Can be set on by the users input bind image.                                                                                                                                                                                                                                                                                                                                                                              |
| Service*                                                                     | PSERVIC byte 4 bit 4.                                                                                                                                                                                                                                                                                                                                                                                                     |
| *Indicates a bind statement which can be set from a user's input bind image. |                                                                                                                                                                                                                                                                                                                                                                                                                           |

VTAM has an IBM-supplied logon mode table which provides generally accepted session protocols for a basic list of IBM device types. This logon mode table can be found in *z/OS Communications Server: SNA Resource Definition Reference*. VTAM presentation services can be specified by the SELECT= parameter on the R(nnnn).PR(m) and R(nnnn).PU(m) initialization statements or the \$T R(nnnn).PR(m) and \$T R(nnnn).PU(m) commands. However, some options are not compatible with all device types.

Although consideration need only be given to the variable statements, the bind image shown below illustrates the JES2 standard session statements. It is not necessary to include these statements in the input bind image.

```
MODEENT LOGMODE=(name),TYPE=X'01',FMPROF=X'03'TSPROF=X'03', C
 PRIPROT=X'B1',SECPROT=X'A3',COMPROT=X'7080', C
 SSNDPAC=X'00',SRCVPAC=X'00',RUSIZES=X'0000', C
 PSNDPAC=X'00',PSERVIC=X'011000009100C00000010040'
```

## Setting Line Density for RJE Devices

You can select the line density for a remote printer by:

1. Specifying the FCBLOAD parameter on either the R(nnnn).PR(m) initialization statement or the \$T R(nnnn).PR(m) operator command.
2. Turning on bit 4 of byte 4 in the PSERVIC field of the JES2 RJE bind image.

This causes JES2 to select the proper density (6 lines per inch or 8 lines per inch).

Certain older printers (for example, the 3777-1 and the 3776-1) cannot have their densities set with PSERVIC's bit 4 of byte 4 set on and require the standard JES2 bind image. If you receive message \$HASP190 at your remote printer, you **must** manually advance the form in the printer to line 1 of the page before starting the printer. This will cause the PSERVIC byte to look like this:

```
PSERVIC=X'011000009900C00000010040'
```

---

## Altering the Sequence of Operations from an RJE Workstation

JES2 provides two parameters that allow the RJE workstation operator to control the sequence of operations at the RJE workstation. One parameter (SUSPEND) allows JES2 to interrupt job output processing, while the other (WAITIME) causes JES2 to wait until it is between print or punch processing. For transmitting either jobs or JES2 commands to the JES2 member that is attached to this RJE workstation, a remote operator can specify:

- The WAITIME= parameter on the \$T RMT(nnnn) command
- The SUSPEND= parameter on either the \$T R(nnnn).PR(m) command or the \$T R(nnnn).PU(m) command

The delay time specified on the WAITIME= parameter takes effect between printing or punching the output of each job. This delay gives the operator the opportunity to ready the card reader and change the terminal status to transmit data. JES2 reads the input stream before resuming printing or punching.

When each BSC hardware terminal printer or punch is defined with SUSPEND=YES on either the R(nnnn).PR(m) statement, the \$T R(nnnn).PR(m) command, the R(nnnn).PU(m) statement, or the \$T R(nnnn).PU(m) command, you can interrupt the printing or punching of jobs by stopping the output device. When the device is again readied by the operator (after transmitting jobs or JES2 commands to the JES2 member), JES2:

1. Simulates an interrupt situation by flushing its current I/O buffers and printing the remote separator page, if one exists.
2. Determines whether the remote card reader is ready.

If the remote card reader is ready, input is read in. If it is not ready, the highest priority output is selected. This output can be the resumption of the current

operation or the start of another data set. The delay must be sufficiently long for the terminal to notify JES2 of the stopped device state. (The time depends on the terminal type.)

If SUSPEND=NO on the remote device, JES2 resumes the current operation after the device is readied again.

For both multileaving terminals and SNA devices, JES2 ignores the SUSPEND= parameter on the R(nnnn).PR(m) and R(nnnn).PU(m) statements; both input and output operations can occur at the same time. For SNA remote devices, operations are not suspended automatically on a time interval. For example, an operator can suspend a data stream being sent to an RJE workstation by issuing the JES2 \$I command.

---

## Pooling RJE Workstations

Remote pooling associates several remotes with a single route code. JES2 supports logical pooling of remote devices and operator consoles in order that the RJE workstations can be used more efficiently. The following explains how installations can use remote pooling to:

- Expand RJE workstations
- Consolidate RJE workstations

JES2 does not allow and cannot resolve multiple levels of remote redirection, that is, you cannot pool a remote to a remote that is already pooled to a second remote. If you attempt to do so, purposely or in error, JES2 issues messages:

1. \$HASP242 - to flag the error
2. \$HASP238 - to indicate the specific remotes that you defined improperly
3. \$HASP441 - to prompt you to terminate JES2 initialization processing and correct the improperly coded RMT(nnnn) ROUTECDE= initialization statements.

## Expanding RJE Workstations

Remote pooling can benefit an installation with an expanding workload by balancing that workload across multiple RJE workstations.

Consider an insurance company office that contains a single printer that receives all the workload. Because of an increasing workload, the company decides to purchase two new RJE workstations (71 and 72), each containing its own printer. The insurance company wants to add these RJE workstations to its installation quickly, without rewriting all their input JCL applications. The solution is remote pooling as shown in Figure 78

In Figure 78, three RJE workstations are pooled simply by adding the ROUTECDE= parameter on the new workstation RMT definitions, thus allowing each workstation to send output to RMT45. Output routed to route code 'R45' can be controlled and printed at any of the three workstations (45, 71, or 72).

RMT(45) RMT(71) ROUTECDE=45 RMT(72) ROUTECDE=45  
*Figure 78. Using Remote Pooling to Accommodate an Expanding Workload*

## Consolidating RJE Workstations

Remote pooling can benefit an installation by allowing the elimination of remote workstations by routing the workload from several remotes to a single remote. In Figure 79 on page 339, two departments of an organization are merging into one. RJE workstation 24 has been removed, so all the work for both departments has

been redirected to the printer at RJE workstation 15. By adding the route code 15 to RJE workstation 24, the installation can avoid changing JCL. As Figure 79 illustrates, the RMT(24) initialization statement remains in the initialization stream, even though RJE workstation 24 no longer exists.

RMT(15) RMT(24) ROUTECDE=15

*Figure 79. Using Remote Pooling to Consolidate Resources*

When previously existing JCL with /\*ROUTE PRINT RMT24 or /\*ROUTE PUNCH RMT24 is submitted, JES2 processing treats the R24 as R15. Similarly, when operators specify the route code R24 in any command, JES2 treats the R24 as R15. Accordingly, before pooling the remotes, systems programmers at this installation must ensure that:

- All jobs have completed execution processing so that output groups have been created.
- All output is routed to the new pooled destination by entering the command.

```
$R ALL,R=R24,D=R15
```

Note that this command will not work once the remotes have been pooled.

If you use a \$T RMT(nnnn) command to modify the ROUTECDE= parameter on RJE workstation 24, you must have previously completed the following procedures:

1. Change all DESTID statements that had been equated with RJE workstation 24 to RJE workstation 15.  
By making these changes through the \$T DESTID(jxxxxxxx) command and the DESTID(jxxxxxxx) initialization statement, you can avoid having to alter JCL.
2. Change the Routecde= specification on all remote devices at your installation to the new RJE remote routing that matches the Routecde= parameter on the RMT statement. (If you desire different routing for individual remote devices than that required for the RJE workstation, you can provide Routecde= parameters that need not match.)
3. Use the \$R command to redirect output and the \$DO command to display the jobs that have gone through execution (with output groups created).

## Using CONDEST= to Specify the RJE Operator Console

Responses to operator commands are made to the RJE workstation that enters the command unless the response is spooled (message spooling). If one of the RJE workstations does not have a console, all responses can be directed to the RJE workstation with a console through the CONDEST= parameter on the RMT(nnnn) initialization statement, the \$ADD RMT(nnnn) command, or the \$T RMT(nnnn) command. The following example shows initialization data set specifications if the console is at RJE workstation 45.

```
RMT(71) CONDEST=45
```

**Note:** On a \$ADD RMT(nnnn) command or a \$T RMT(nnnn) command, you cannot specify a CONDEST= value higher than the RMTNUM= value on the TPDEF initialization statement. If you specify a higher CONDEST= value, JES2 responds with an error message.

Specifying CONDEST= also allows the operator at either remote work station to control both devices and jobs whose output is routed back to either RJE workstation. However, the remote that receives the responses to the commands is the remote specified in the CONDEST= parameter.

If the RJE workstation has pooled remote printers, JES2 routes spooled responses to either remote printer.

---

## Remote Message Spooling

When JES2 cannot send a message directly to a remote console device, the member writes the message to spool for later printing by a remote printer. JES2 might not be able to send a message to a remote console because:

- A remote console is not defined for that RJE workstation

[CONS=NO on the RMT(nnnn) initialization statement, \$ADD RMT(nnnn) command, or the \$T RMT(nnnn) command.]

- The number of messages already queued for an RJE workstation exceeds the RMTMSG= parameter on the TPDEF initialization statement.
- The RJE workstation is not currently signed on.

When JES2 spools remote messages, it creates a special **job** to represent the spooled remote message data set. This **job** is created as a started task with a job name equal to the remote name. Therefore, this data set can be displayed or purged by operator commands.

The following limitations apply to operator commands entered against remote messages:

- The \$R command cannot be used to route remote messages.
- The \$DO command cannot be used to list the status of remote messages.
- A \$C or \$P command will be rejected if the remote message data set is currently being processed (that is, if messages are being queued or printed).

If additional messages are added to an existing spooled message data set, the same remote message job is used, and the messages are added to the end of the data set.

**Note:** Remote message jobs are automatically moved from a spool volume affected by the dynamic spool deletion commands, \$P SPL and \$Z SPL.



---

## Part 7. Providing Security for JES2

|                                                              |     |
|--------------------------------------------------------------|-----|
| <b>Chapter 7. Providing Security for JES2</b>                | 343 |
| Security Authorization Facility (SAF) of MVS                 | 344 |
| Using RACF to Provide Security                               | 344 |
| JES2 Access to Resources                                     | 344 |
| Securing Resources                                           | 344 |
| SMF Record Summary: RACF Security                            | 347 |
| Defining and Grouping Your Installation's Support Personnel  | 347 |
| Specifying Access Authority                                  | 348 |
| Universal Access Authority                                   | 348 |
| Access Lists                                                 | 348 |
| Security Labels                                              | 348 |
| Controlling Access to Data Sets JES2 Uses                    | 349 |
| Controlling Input to Your System                             | 349 |
| How RACF Validates Users                                     | 350 |
| Controlling Job Submission and Cancellation                  | 351 |
| Authorizing Users to Submit Jobs for Other Users             | 351 |
| Authorizing the Use of Input Sources                         | 352 |
| Authorizing Work from Remote Job Entry (RJE) Workstations    | 352 |
| Authorizing Networking Jobs and SYSOUT (NJE)                 | 353 |
| Authorizing Inbound Work                                     | 353 |
| Understanding Networking Profiles                            | 354 |
| Authorizing Jobs                                             | 355 |
| Authorizing SYSOUT                                           | 356 |
| Validating SYSOUT Based on the Submitter                     | 356 |
| Understanding Default Userids                                | 356 |
| Translating Security Information                             | 358 |
| Authorizing Inbound SYSOUT by Translating the Default Userid | 358 |
| How JES2 Propagates Security Information                     | 358 |
| Defining Nodes as Local SYSOUT Sources                       | 359 |
| Authorizing Outbound Work                                    | 359 |
| Controlling Access to Data that Resides on Spool             | 359 |
| Controlling Access to SYSIN and SYSOUT                       | 359 |
| SPOOL Browse access to SYSIN and SYSOUT                      | 360 |
| Protecting JESNEWS                                           | 361 |
| Protecting Trace Data Sets                                   | 362 |
| Protecting SYSLOG                                            | 362 |
| Protecting Spool Offload Data Sets                           | 362 |
| Controlling Where Output Can Be Processed                    | 363 |
| Controlling External Writers                                 | 364 |
| Authorizing the Use of Operator Commands                     | 364 |
| Considerations for Automatic Commands                        | 372 |
| Using JES2 to Provide Security                               | 372 |
| JES2 Initialization Statements                               | 372 |
| JES2 Security Exit Points                                    | 374 |
| Multiple Levels of a Security Product in a MAS               | 375 |



---

## Chapter 7. Providing Security for JES2

Security in a data processing environment involves controlling and auditing access to resources that are important to your installation. These resources include:

- JES2-owned data sets (spool, checkpoint, and module libraries)
- Input (nodes, RJE workstations, readers, internal readers, and offload devices)
- Job names
- Data sets residing on spool (SYSIN/SYSOUT)
- Output devices (nodes, printers, punches, RJE workstations, and offload devices)
- Command input

JES2 provides a basic level of security for some of these resources through initialization statements. Additionally, JES2 provides information to the security authorization facility (SAF) at various points during its processing. This interface to SAF allows you to use RACF to provide any additional control and auditing your installation might require. When SAF returns control to JES2, JES2 enforces any security decisions SAF returns.

You and your security administrator should plan your security as you would any additional facility you would add to your JES2 system. The plan should address questions such as the following:

- What resources must I protect?
- Should I restrict jobs and users from certain information depending on other criteria (security labels)?
- Should I limit the job names users can submit or cancel?
- Is it important to protect SYSIN and SYSOUT?
- Which remote workstations should access my system?
- Can other nodes submit jobs to my system?
- To which nodes should I allow my system to send data?
- Should I limit the commands an operator can use?
- Do I want to restrict the consoles an operator can use to enter certain commands?
- What commands will I allow jobs, workstations, and nodes to submit to my system?
- Do I want only selected output devices to process particular output?
- Should the security label of the output appear on the header pages?

Minimally, use initialization statements to control the work that input devices can input to your JES2 system. JES2 exits can add another level of security to your JES2 system. However, you can implement a more complete security policy by using the SAF interface to RACF.

Each additional resource you protect could affect the overall performance of your JES2 system. Therefore you should discuss the resources you are protecting, the frequency of their use, and your performance goals with your security administrator to determine the best overall plan for your installation. Additional information about planning security appears in the *z/OS SecureWay Security Server RACF Security Administrator's Guide*.

---

## Security Authorization Facility (SAF) of MVS

During its processing, JES2 will pass information to the security authorization facility (SAF) to perform password validation, to request authority to access a resource, to build or obtain a security token for a resource, or to determine security information in a certain environment. When SAF receives the request, it determines if RACF is active. If RACF is active, SAF passes the request to RACF; if RACF is not active, SAF returns immediately to JES2 with a response indicating that SAF could not validate the request and any existing JES2 security processing controls the resource. “Using JES2 to Provide Security” on page 372 describes the existing JES2 security processing. When SAF indicates a decision on a security request, JES2 bypasses its own security processing.

In your exit routines, you can use JES2 macros to place additional calls to SAF. The exit routines can do security processing. The JES2 exits to be used are:

- Exit 36 (Pre-security Authorization Call)
- Exit 37 (Post-Security Authorization Call)
- Exit 38 (TSO/E Receive Data Set Disposition)
- Exit 39 (NJE SYSOUT Data Set Disposition)

See *z/OS JES2 Installation Exits* for information about the security exits, macros, and invoking SAF in your exit routines.

---

## Using RACF to Provide Security

The following sections discuss securing your system with RACF Release 1 Version 9 or higher installed. Generally, JES2 operates as it did previously if you have RACF Release 1 Version 8 or earlier installed on your system except for the RACF NOEARLYVERIFY option which is no longer a valid option for JES2; all jobs are verified during input service.

### JES2 Access to Resources

JES2 uses many resources. Be certain JES2 has enough authority to access every resource it requires. **Your RACF support personnel must define JES2 in the RACF started procedures table with the trusted attribute so JES2 has access to every resource it might use.** The name you supply to your administrator is in member IEFSSNxx of SYS1.VnRnMn.SHASPARM. The following sections discuss the resources you can control, the value of controlling the resource, a methodology for controlling the resource, and how to control the resource using RACF.

### Securing Resources

You or your RACF administrator can secure your JES2 resources by creating RACF resource profiles. Each profile (or generic profile) contains:

- The name that identifies a resource or group of resources
- The class of the resource
- The availability of the resource to all users
- A list of userids or groupids that can access the resource and their authorization level, if needed
- An optional security label for the resource
- Other security-related information.

The profile name identifies a resource or set of resources to RACF. The name that identifies a resource to JES2 (defined in the initialization data set) is the basis of the profile name your RACF administrator uses to define the RACF profile.

Your security administrator defines different types of resources (printers, nodes, and SYSOUT, for example) to different RACF classes. Table 69 shows the JES2 resource type and the class(es) your RACF administrator can use to define the resource.

*Table 69. JES2 Resources and Associated RACF Classes*

| <b>JES2 Resource</b>                                                                                                                                                                                                                                                      | <b>RACF Profile Name Format</b>                                                                                                                                                                                                                                          | <b>RACF Class(es)</b>         | <b>Class Purpose</b>                                 |
|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------|------------------------------------------------------|
| Commands from Network Job Entry (NJE) Nodes                                                                                                                                                                                                                               | NJE.nodename<br>jesname.command[.qualifier]<br>node.RUSER.userid                                                                                                                                                                                                         | FACILITY<br>OPERCMDS<br>NODES | Allows a node to issue commands to your system       |
| Commands from RJE Workstations                                                                                                                                                                                                                                            | jesname.command[.qualifier]                                                                                                                                                                                                                                              | OPERCMDS and FACILITY         | Restrict commands to authorized users                |
| Data sets JES2 uses <ul style="list-style-type: none"> <li>Initialization data set</li> <li>Spool data sets</li> <li>Checkpoint data sets</li> <li>Procedure libraries</li> <li>Module libraries</li> <li>Parameter libraries</li> <li>Spool offload data sets</li> </ul> | 'data set name'                                                                                                                                                                                                                                                          | DATASET (always active)       | Prevents unauthorized access to data sets            |
| Data Sets Residing on Spool <ul style="list-style-type: none"> <li>SYSIN</li> <li>SYSOUT</li> <li>JESNEWS</li> <li>Trace data sets</li> <li>SYSLOG</li> </ul>                                                                                                             | localnodeid.userid.jobname.jobid.dsnumber.name<br>localnodeid.userid.jobname.jobid.dsnumber.name<br>localnodeid.jesid.\$JESNEWS.STCtaskid.DnewsIvI.JESNEWS<br>localnodeid.jesname.\$TRCLOG.taskid.dsnumber.JESTRACE<br>localnodeid.+MASTER+.SYSLOG.jobid.dsnumber.SYSLOG | JESSPOOL                      | Restrict access to data on spool to authorized users |

Table 69. JES2 Resources and Associated RACF Classes (continued)

| JES2 Resource                                                                                                                                                                                                                                                                                 | RACF Profile Name Format                                                                                                                                                                                                                      | RACF Class(es)      | Class Purpose                                                                                                                           |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| Input Sources <ul style="list-style-type: none"> <li>• Readers</li> <li>• Internal Readers (INTRDR)</li> <li>• STCINRDR</li> <li>• TSUINRDR</li> <li>• Remote Job Entry (RJE) Workstations</li> <li>• Network Job Entry (NJE) Nodes<sup>1</sup></li> <li>• Spool Offload Receivers</li> </ul> | <ul style="list-style-type: none"> <li>• RDRnn as defined on the RDR(nn) initialization statement</li> <li>• INTRDR</li> <li>• STCINRDR</li> <li>• TSUINRDR</li> <li>• OFFn.SR and OFFn.JR as defined in the initialization stream</li> </ul> | JESINPUT (see note) | Restricts users submitting specific jobs to specific devices                                                                            |
| Job submission and cancellation                                                                                                                                                                                                                                                               | SUBMIT.localnodeid.jobname.userid<br>CANCEL.localnodeid.userid.jobname                                                                                                                                                                        | JESJOBS (see note)  | Controls which jobnames and userids users can use when submitting or cancelling jobs. Can also control which users can submit any jobs. |
| Local Commands                                                                                                                                                                                                                                                                                | jesname.command[.qualifier]                                                                                                                                                                                                                   | OPERCMDS            | Restrict commands to authorized users                                                                                                   |
| Network Job Entry (NJE) Nodes                                                                                                                                                                                                                                                                 | nodeid.keyword.entity*.                                                                                                                                                                                                                       | NODES               | Prevent processing of unauthorized jobs or sysout from another node                                                                     |
| Output Devices <ul style="list-style-type: none"> <li>• Local and FSS devices</li> <li>• RJE devices</li> <li>• NJE devices</li> <li>• Spool Offload Transmitters</li> </ul>                                                                                                                  | jesname.LOCAL.devicename<br>jesname.RJE.devicename<br>jesname.NJE.nodename                                                                                                                                                                    | WRITER              | Restrict processing of output to specific devices                                                                                       |
| Remote Job Entry (RJE) Workstations                                                                                                                                                                                                                                                           | RJE.workstation-id                                                                                                                                                                                                                            | FACILITY            | Prevent unauthorized sign-on by remotes                                                                                                 |

Table 69. JES2 Resources and Associated RACF Classes (continued)

| JES2 Resource                                                                                                                                                                                                     | RACF Profile Name Format | RACF Class(es) | Class Purpose                                           |
|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------|----------------|---------------------------------------------------------|
| Update JESNEWS                                                                                                                                                                                                    | jesname.UPDATE.JESNEWS   | OPERCMDS       | Restrict ability to create, update, and delete JESNEWS. |
| <b>Note:</b> At least one profile that defines all jobs must exist in this class when this class is active or all jobs will fail.<br><sup>1</sup> See “Authorizing Networking Jobs and SYSOUT (NJE)” on page 353. |                          |                |                                                         |

When RACF is active, every user must have a RACF **user profile**, any class in use must be active, and all resources you want to protect must have a resource profile (except those in the JESSPOOL class). Before JES2 completes a request for a resource from a user, JES2 requests authorization from SAF. SAF passes the request to RACF which determines the authority based on the existing profiles. If RACF is not active or cannot determine the authorization for a resource, JES2 carries out its own security processing, if any, for that resource. The *z/OS SecureWay Security Server RACF Security Administrator's Guide* has additional information about profiles and access.

## SMF Record Summary: RACF Security

The following lists the SMF record written when RACF provides security for your JES2 subsystem. For a complete list of the record contents, see *z/OS MVS System Management Facilities (SMF)*.

Table 70. SMF Records Used by JES2 with RACF Security

| Record Number | Action that Causes the Record to be Written                                                                                                                                                            |
|---------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 80            | <ul style="list-style-type: none"> <li>An unauthorized attempt to access the system.</li> <li>Any attempt to access a RACF-protected source.</li> <li>Any attempt to modify a RACF profile.</li> </ul> |

## Defining and Grouping Your Installation's Support Personnel

System programmers and operators (the support personnel) at your installation need to be defined to RACF. Your installation's security administrator must define any personnel who:

- Issues JES2 or MVS commands
- Updates data sets JES2 uses.

You can group your installation's support personnel into groups that are responsible for a particular area. For example, you might want to group your support personnel by shift, by functional area, or by both criteria. If you want, your security administrator can define your support personnel to RACF in groups. Therefore, you might want to consider combining users into groups and assigning a unique identifier to each group.

To group your installation's support personnel you should:

- List the userids (or names of proposed userids if not already defined) of all the system programmers and operators at your installation
- Group any of the userids together if they:



- Perform similar tasks
- Work on the same shift

You will want to keep a record of userids and groupids available for use in securing other system resources such as spool data, console access, and commands as well as for updating groups in the future.

## Specifying Access Authority

RACF allows you to permit access to resources with:

- Universal access authority (UACC)
- Access lists

### Universal Access Authority

The universal access authority assigned to each resource defines the access that all users have to a resource unless the users are in the access list. The meaning of the universal access authorities varies depending on the type of resource that is being defined. For example, the following UACC values are valid for resources defined through the RACF DATASET class:

**NONE** Specifies that the user or group of users is not permitted to access the resource.

#### EXECUTE

Specifies a user can load and execute a program from a private program library but cannot read or copy the program. This access authority applies only if you have installed Version 3 Release 1 or a subsequent release of the MVS Data Facility Product (5665-XA3).

**READ** Specifies the user can read from the resource.

#### UPDATE

Specifies the user can read from or write to the resource.

#### ALTER

Specifies a user the maximum access RACF allows to the resource and permits a user to update a discrete profile.

For example, if you assign a UACC value of READ to a data set named WORKLOAD, then all users would be able to read the data set. However, users could not update WORKLOAD unless they were explicitly allowed to do so through an access list.

### Access Lists

You can define exceptions to the universal access authority assigned to a resource by defining the authority of a user or group in an access list associated with a resource. For example, you can assign a UACC value of READ to WORKLOAD and assign a access value of UPDATE to userid TOMN. In this case, TOMN would be able to write to WORKLOAD. The authority granted to a user or group of users through an access list effectively overrides the universal access authority associated with a resource. Refer to *z/OS SecureWay Security Server RACF Security Administrator's Guide* information about defining access authority.

## Security Labels

You can add another layer of control for your resources through security labels (through the RACF SECLABEL class). Security labels allow an installation to restrict personnel who can view data from copying that data to a less secure device or data

set. Also, users with the authority to view a group of data could be restricted from viewing more vital pieces within that group through the use of security labels and profiles.

When the SECLABEL class is active, each user must specify the security label for a session or job (or use the default SECLABEL established in the USER profile) to be able to access data that has a security label. (A user can have more than one security label associated with a userid but can only specify one for a session or job.) RACF determines whether the user's security label for the session is equal to or greater than the security label of the data the user is accessing before verifying if the user has authority to view the data. The highest security label in the system is **SYSHIGH**, the lowest is **SYSLOW**. Your installation should define as many levels of security labels between SYSHIGH and SYSLOW as needed to implement your installation's security policy.

If you receive SYSOUT data sets that contain an unknown or blank SECLABEL and your node has an active SECLABEL class, JES2 assigns this SYSOUT the SECLABEL RACSLUNK. Because your installation has not predefined this SECLABEL, no one can access the SYSOUT.

You can make the SYSOUT accessible by:

- Defining RACSLUNK to RACF as a valid SECLABEL and authorizing users.
- Using the NODES class translation facility to translate RACSLUNK to a predefined SECLABEL.

Your installation's security policy could require security labels for all users and resources. Your security administrator enforces this policy by activating various RACF classes and options. For more information on security labels, see *z/OS SecureWay Security Server RACF Security Administrator's Guide*.

## Controlling Access to Data Sets JES2 Uses

The JES2 spool and checkpoint data sets are critical for proper operation of your JES2 system. It is critical that JES2 be the only user that can update the information in these data sets. However, it is also important for a limited group of users to be able to recreate the spool and checkpoint data sets (should the data set become unusable because of hardware problems). Also, restrict access to the data set that contains the modules that JES2 uses. Make sure profiles exist for any data sets you might use for checkpoint reconfiguration.

Your RACF administrator (or you) would define profiles for the data sets involved to the DATASET class and permit the users that must have access to the data sets to the DATASET profile just created. Define **discrete profiles** for all your spool and checkpoint data sets. This protects them from unauthorized access even when not in use.

See *z/OS SecureWay Security Server RACF Command Language Reference* for more information about discrete profiles.

## Controlling Input to Your System

There are many ways a job can enter the system. RACF can:

- Validate the security information for job and data entering the system from any reader, internal reader (INTRDR, STCINRDR, and TSUINRDR), RJE workstation, NJE node, and spool offload receiver. If RACF is available, SAF propagates missing security information to the submitted job (or data) for validation.

- Limit the users authorized to submit jobs to the system.
- Restrict the job names a user can submit or cancel.
- Restrict the userids a user can use to submit or cancel jobs.
- Authorize a userid to submit or cancel any jobs.

### **How RACF Validates Users**

Use RACF to prevent unauthorized users from accessing your system or running batch jobs. Your RACF security administrator can indicate to RACF that any batch job requires a valid userid, password, and, optionally, security label on the JOB statement or propagated security information. Your administrator can also define what security information must be present for any data or user to enter your system.

JES2 issues a request to RACF to validate a job's security label, userid, groupid, and password when a job enters the system from any source. This ensures that JES2 does not process any unauthorized work.

As a result, the submitter becomes aware of any authorization errors almost immediately (prior to JCL conversion) rather than waiting until JES2 selects the job for execution. For example, during a TSO/E session a user issues the TSO/E SUBMIT command to enter a job into the system, if the job fails an authorization check, JES2 notifies the user, queues the job for the JES2 output or purge processing and flushes the job from the system.

***Propagation of Security Information:*** If RACF is active and a job enters the system with some or all security information missing, SAF propagates the submitter's security information to the job. For example, if JOB1 submits JOB2, and JOB2 does not have SECLABEL= specified on the JOB JCL statement, SAF passes the value of SECLABEL= from JOB1's JOB statement to JOB2.

Any user in a currently active session (TSO/E, executing batch job or INTRDR) can have SAF propagate the security information associated with the session by omitting the information on the JOB statement for the job. If SAF can not determine the group or Security label information from the current session, SAF uses the default information in the RACF profile. However, SAF will not propagate security information to a job that enters the system from an RJE workstation or a physical card reader.

***Propagating Security Information Across a Network:*** To allow users to submit jobs without specifying security information such as a userid, JES2 propagates the submitter's security information when the information is omitted. For example, you can have users omit their password from their job statements if you do not want to send passwords through the network. Propagation also occurs when you use the /\*XMIT card to transmit a job to another node in the network. In this case, SAF passes the information that appears in the first JOB statement to the JOB statement that follows the /\*XMIT card.

If SAF is unable to verify the security information on the first JOB statement:

- If a TSO/E user submitted the job, SAF passes the TSO/E user's security information to the second JOB statement
- If the job entered the system through a local card reader, SAF uses a default userid for propagation purposes. (See "Understanding Default Userids" on page 356 for information about the default userid.)

"How JES2 Propagates Security Information" on page 358 describes what security information RACF propagates for NJE jobs.

## Controlling Job Submission and Cancellation

Your installation might want to control the users who can submit or cancel certain jobs. For example, you might want only specific people in your accounting department to submit the job that processes the payroll. By defining the jobname in class JESJOBS and a list of users authorized to submit the job to RACF, SAF can determine if the user submitting (or cancelling) the job has the authority to do so. The format of the RACF profile name for jobs is:

`SUBMIT.nodename.jobname.userid`

or

`CANCEL.nodename.userid.jobname`

where:

### **SUBMIT**

Controls which users can submit jobs.

### **CANCEL**

Controls which users can cancel jobs.

### **nodename**

The name of the node on which the submit or cancel will occur.

### **jobname**

The job name you are securing.

**userid** The userid associated with the job you are securing.

You do not need a profile for a user to submit or cancel jobs that have their own userid on the JOB statement. When you grant a user the ability to submit a job, you should permit that userid to the profile with an access level of READ. When granting access to cancel a job, you must permit the userid to the profile with an access level of ALTER.

The UACC and access lists associated with these profiles also allow you to control which userids a user can use on JOB statements or whether the user can submit or cancel any jobs. See *z/OS SecureWay Security Server RACF Security Administrator's Guide* for additional information on controlling job submission and cancellation.

## Authorizing Users to Submit Jobs for Other Users

Your RACF administrator can allow users to submit jobs on behalf of other users without compromising the password of the user whose jobs are being submitted. This feature is particularly useful when a person is assuming a production workload for someone going on vacation or a leave of absence.

Your RACF administrator must define the userid of the person who will be submitting the jobs in the RACF SURROGAT class. Once this is done, the user just submits the job with the original userid and without a password on the JOB card. RACF then validates the job(s) as if the original user had submitted it and will use that userid's password and default security information when verifying the jobs authority for resources.

See *z/OS SecureWay Security Server RACF Security Administrator's Guide* for information about the SURROGAT class.

## Authorizing the Use of Input Sources

You can use RACF to limit which sources of input are valid for job submission, including RJE workstations, device readers, nodes, and internal readers. For example, you might want to prevent certain users from entering jobs from a particular RJE workstation.

To authorize the submission of work from specific input sources, ask your security administrator to activate the RACF JESINPUT class and define a profile for each input source. Provide your security administrator with the following information:

- The name of the device. Table 71 lists the names to use for each type of input device.

Table 71. Device Names to Use for RACF Profiles

| Input Source:                                              | Device Name:                                                                                 |
|------------------------------------------------------------|----------------------------------------------------------------------------------------------|
| NJE (Jobs and SYSOUT)                                      | adjacent node name (specified on NODE(nnnn) statement)                                       |
| Internal readers (other than started tasks or TSO/E logon) | INTRDR                                                                                       |
| Internal readers for started tasks                         | STCINRDR                                                                                     |
| Internal readers for TSO/E logon                           | TSUINRDR                                                                                     |
| Device Readers                                             | Use same name as specified on the RDR(nn) initialization statement.                          |
| RJE workstations                                           | Rnnnn.RDm where devname is the name specified on the R(nnnn).RD(m) initialization statement. |

- The userid or groupid of the users you want to authorize or restrict.
- The universal access authority to associate with each device. Valid access values for input devices are:
  - NONE** Specifies that only those users explicitly permitted through the access list can use the input device.
  - READ** Specifies that only those users assigned an access authority of read, update, or control can use the input device.

A user must have READ access to a device (either through the UACC or explicitly in an access list) in order to use a input device. If the device has a UACC of READ, you can restrict users from a device by listing them in an access list and specifying NONE for their access.

**Note:** By default, JES2 accepts all work from an input source when the RACF JESINPUT class is inactive.

## Authorizing Work from Remote Job Entry (RJE) Workstations

Operators at RJE workstations must issue either a /\*SIGNON (if BSC) or a LOGON (if SNA) statement before JES2 establishes a session with the remote. In RACF, the administrator defines the workstation ID used in the /\*SIGNON statement in a profile name in the FACILITY class. When properly defined, this allows the remote access to your system. For example, the profile name for a workstation with the ID RMT1 is:

RJE.RMT1

The administrator must also define the remote workstation as a valid RACF userid for RACF to control the signon process and any commands from the remote.

JES2 passes the workstation ID and the password specified to RACF for userid validation during sign-on processing. RACF requires the password be present during sign-on processing for all remote workstations it controls. If RACF is active, RACF performs the userid validation for the remote. If RACF is not active, JES2 performs the userid validation for the remote using the line and remote password specified in the JES2 initialization stream or set by the system operator. The UACC of the remote should be READ.

The password for an RJE workstation must be changed the first time the workstation issues a logon or signon. Otherwise, RACF will reject the access attempt.

## Authorizing Networking Jobs and SYSOUT (NJE)

This section contains information about how to use RACF to ensure that all work entering or leaving your node complies with your installation's security policy. You can control:

- Jobs and data received from other nodes in a network.
- The extent of security validation performed at your node.
- Jobs and data destined for other nodes in a network.

JES2 does not validate work passing through your node on its way to another node in the network, but it does protect the work from unauthorized access while the work is temporarily stored at your node.

To provide security for Networking Job Entry (NJE), have your security administrator activate the RACF NODES class (for inbound work) or the RACF WRITER class (for outbound work), and define the profiles needed to enforce your installation's networking security policy. As with other RACF-protected resources, you must provide your security administrator with specific information needed to define profiles.

Before you can provide this information, you must first decide whether you want to protect inbound work, outbound work, or both. For inbound work, you must decide whether you want to protect jobs, SYSOUT, or both. You must also determine which users or groups of users you will allow to submit work, and the security labels that are valid for processing on your node.

If a WRITER class profile does not release SYSOUT to a device, JES2 does not issue a message. To issue messages, refer to Exit 36 in *z/OS JES2 Installation Exits*.

### Authorizing Inbound Work

The following topics identify what functions RACF provides and the information that you should provide to your security administrator to activate those functions. This section provides information about the following concepts and tasks:

- ***Understanding Networking Profiles*** explains how the values you select for the RACF NODES profile determines what type of work and which users you want validated.
- ***Authorizing Jobs*** explains how you can use RACF to validate inbound jobs from other nodes in a network.
- ***Authorizing SYSOUT*** explains how you can use RACF to validate inbound job output (SYSOUT) from other nodes in a network.
- ***Translating Security Information*** explains how RACF can be used to replace inbound userids, groupids, or security labels with locally-defined values.



- **Validating Work Based on the Submitter** explains how RACF can be used to validate inbound work using the submitter's security information instead of the owner's security information.
- **Understanding Default Userids** describes how JES2 handles security information for work from incompatible nodes and explains how JES2 handles security information belonging to store-and-forward work. This section also describes how you can use RACF to manipulate default security information.
- **How JES2 Propagates Security Information** explains where JES2 obtains missing security information for NJE work.
- **Defining Nodes as Local Input Sources** explains how you can use RACF to treat work from another node as if the work originated at the home node.

## Understanding Networking Profiles

The values that you specify in networking profiles determine how RACF validates inbound work. As with other RACF profiles, this profile consists of a profile name, profile class, and a universal access authority value. All networking profiles for inbound work are associated with the RACF NODES class. The profile name is a 3-part identifier that indicates the origin of the work and the type of security information you want validated. The universal access value determines the actions that RACF performs on the inbound work.

A NODES profile name has the following format:

`nodeid.keyword.name`

where:

### **nodeid**

The name of the node from which you expect inbound work.

### **keyword**

The type of work (job or SYSOUT) entering from the node and the security attributes (userid, groupid, or security label) you want RACF to examine. The last character, J or S, indicates the type of work entering your system. Allowable values are USERJ, USERS, GROUPJ, GROUPS, SECLJ and SECLS for userid, groupid, and security label examination respectively.

**name** The actual userid, groupid, or security label you are controlling. These values must either be defined in your RACF data base or you can define profiles that translate these values into acceptable values for your system.

For example, the following profile:

`BERMUDA.USERJ.WAYNE`

controls whether jobs coming from userid WAYNE at node BERMUDA can execute here. You can optionally associate a local userid with userid WAYNE through the profile. Information about associating local security information with inbound work is contained in "Translating Security Information".

You can place an asterisk in any position of a profile to control a wider range of work. For example, if you place an asterisk in place of the nodeid value, RACF performs the requested type of validation for work from all nodes in the network. For information about using generic profiles see, *z/OS SecureWay Security Server RACF Security Administrator's Guide*, SA22-7683.

If you have installed Version 1 Release 9 of RACF and do not activate the RACF NODES class, JES2 validates jobs and SYSOUT in the following manner:



- JES2 runs only those jobs that have a valid userid and password.
- A security label of SYSHIGH is assigned to all SYSOUT destined for your node and can be printed on only those devices permitted to SYSHIGH data. JES2 assigns the default userid to this SYSOUT. See “Understanding Default Userids” on page 356 for information about default userids.
- All work destined for another node remains unchanged.

If you choose to activate the NODES class, you must provide your security administrator with the appropriate profile information to control the work entering your system. The following sections identify the appropriate values for each type of work.

### Authorizing Jobs

You can control which network jobs are authorized for processing at your installation based on the userid, groupid, or security label associated with the inbound job.

To authorize or restrict jobs entering your system from another node, ask your security administrator to define a NODES profile that specifies the criteria upon which jobs are accepted. Provide your security administrator with the following information:

- The node name from which you expect jobs.
- The userid or groupid from which you expect jobs.
- The security labels that you will accept.
- The universal access value, which determines how JES2 will process the job. Table 72 lists the universal access values you can assign and defines the validation that RACF performs.

Table 72. NODE Class Keywords and the UACC Meaning for Inbound Jobs

| Type of Check<br>(keyword) | UACC          |                                                                                                                |                                                                                                                                                                    |                                                                                                                                                                                          |
|----------------------------|---------------|----------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                            | NONE          | READ                                                                                                           | UPDATE                                                                                                                                                             | CONTROL or greater                                                                                                                                                                       |
| userid<br>(USERJ)          | Fails the job | Verifies all security information available including password validation.                                     | If non-default valid security information exists, uses the submitter's or translated security information as the owning security information without revalidation. | Same as UPDATE, but default security information is allowed. CONTROL allows a pre-SP3.1.3 system to send jobs to your node without passwords. RACF does not perform password validation. |
| groupid<br>(GROUPJ)        | Fails the job | Translates GROUPID to that specified in ADDMEM. If ADDMEM is not specified, uses the groupid received.         |                                                                                                                                                                    |                                                                                                                                                                                          |
| security label<br>(SECLJ)  | Fails the job | Translates SECLABEL to that specified in ADDMEM. If ADDMEM is not specified, uses the security label received. |                                                                                                                                                                    |                                                                                                                                                                                          |

#### Notes:

1. RACF can perform only userid, groupid, and password validation for jobs entering from a pre-SP3.1.3 system because SECLABELS do not exist for pre-3.1.3 systems.
2. If no profile exists for a job when the NODES class is active or if the RACF NODES class is inactive, RACF performs only userid, groupid, and password validation without performing any translation.

## Authorizing SYSOUT

You can control the processing of SYSOUT at your installation based on the userid, groupid, or security label associated with the inbound SYSOUT.

If when running in warm mode, you receive message \$HASP186 indicating an access violation [to devices, external writers, or SYSOUT Application Programming Interface (SAPI) requests], and you require further diagnostic information, set `DEBUG SECURITY=YES` and refer to *z/OS JES2 Diagnosis*.

To authorize or restrict SYSOUT entering your system from another node, ask your security administrator to define a profile that identifies the criteria upon which SYSOUT is accepted. Provide your security administrator with the following information:

- The node name(s) from which you expect SYSOUT.
- The userid(s), groupid(s), and security labels from which you expect SYSOUT.
- The universal access value, which determines how RACF assigns an owner to the SYSOUT. RACF can assign ownership based on either the userid and node that created the SYSOUT or the userid and node that submitted the job that created the SYSOUT. Table 73 on page 357 shows the universal access values you can assign and defines the validation that RACF performs.

## Validating SYSOUT Based on the Submitter

JES2 normally validates SYSOUT based on the owner's security information. The owner's security information accompanies each piece of SYSOUT as it travels through the network.

You can have your security administrator define profiles that cause RACF to assign ownership of the SYSOUT to the submitter. For example, you can allow a user to submit a job to another node, have the job execute under another userid, and allow the submitting user to view the output upon its return.

To translate inbound work ownership to the submitter, specify `&SUSER` as the value of the `ADDMEM` keyword of the RACF `NODES` profile for the inbound SYSOUT. For example, the profile:

```
RDEFINE NODES GOTHAM.USERS.NAPIER ADDMEM(&SUSER) UACC(UPDATE)
```

causes ownership of all SYSOUT created at node GOTHAM by userid NAPIER to be assigned to the userid that submitted the creating job.

## Understanding Default Userids

RACF assigns a default userid to all work that enter your node when:

- SYSOUT enters from a non-JES2 system, unless translated to a valid userid by a `NODES` class profile
- SYSOUT enters from a pre-JES2 SP3.1.3 system, unless translated to a valid userid by a `NODES` class profile
- SYSOUT enters from a JES2 SP3.1.3 or later member that uses an earlier release of RACF (that is, earlier than Version 1 Release 9 of RACF), unless translated to a valid userid by a `NODES` class profile
- SYSOUT enters from a JES2 SP3.1.3 or later member and RACF 1.9, but RACF is inactive, unless translated to a valid userid by a `NODES` class profile
- SYSOUT enters from a another node and RACF 1.9 is not installed or active at your node

- Your node is an intermediate (store-and-forward) node on the path to the work's final destination. The default userid protects work while it resides on spool awaiting transmission.

RACF uses eight question marks (????????) as the userid for all inbound work meeting the above criteria. Your security administrator can assign a different userid using the RACF SETROPTS command. For example, if you want to process any of these jobs locally, you can define a single userid to which all of these undefined userids are translated. You can then permit that translated userid to specific resources. You can not directly permit the default userid (either IBM-supplied or installation-defined) to any resources. See *z/OS SecureWay Security Server RACF Security Administrator's Guide* about defining default userids for NJE work that meet the criteria.

Table 73. NODES Class Keywords, UACC, and SYSOUT Ownership when Execution Node is Not Defined to &RACLNDE

| Type of Check (keyword)                                                                                                                 | UACC                                                                                                                |                                                                                                                                                          |                                                                                                                                                                                                                                                                                            |                                                                                                                                                                                                             |
|-----------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                                                                                                                         | NONE                                                                                                                | READ                                                                                                                                                     | UPDATE                                                                                                                                                                                                                                                                                     | CONTROL or greater                                                                                                                                                                                          |
| userid (USERS)                                                                                                                          | <b>Check of Userid and Node that Created SYSOUT</b>                                                                 |                                                                                                                                                          |                                                                                                                                                                                                                                                                                            |                                                                                                                                                                                                             |
|                                                                                                                                         | Purges the output.                                                                                                  | If the translation value from ADDMEM specifies &SUSER, check submitting userid and node.<br><br>Otherwise, assigns ownership of the output to ?????????. | If default or no security information is available, processing is the same as a UACC of READ.<br><br>If security information is valid, assigns the translation value from ADDMEM to the output. When ADDMEM is not specified, ownership is assigned to the userid that created the output. | Processing is similar to UACC(UPDATE) except RACF translates any available information. This allows RACF to assign local userids to output from pre-SP3.1.3 nodes.                                          |
|                                                                                                                                         | <b>Check of Submitting Userid and Node (only when &amp;SUSER is specified for ADDMEM in execution node profile)</b> |                                                                                                                                                          |                                                                                                                                                                                                                                                                                            |                                                                                                                                                                                                             |
|                                                                                                                                         | Assigns ownership of the output to ?????????.                                                                       | Assigns ownership of the output to ?????????.                                                                                                            | Assigns ownership of the output to ?????????.                                                                                                                                                                                                                                              |                                                                                                                                                                                                             |
|                                                                                                                                         |                                                                                                                     |                                                                                                                                                          |                                                                                                                                                                                                                                                                                            | Assigns the translation value from ADDMEM to the output, if available. If translation value is &SUSER, assigns the submitter userid to the output. Otherwise, assigns ownership of the output to ?????????. |
| <b>Note:</b> When you specify &SUSER for ADDMEM and the submitting node is defined to &RACLNDE, ownership is assigned to the submitter. |                                                                                                                     |                                                                                                                                                          |                                                                                                                                                                                                                                                                                            |                                                                                                                                                                                                             |
| groupid (GROUPS)                                                                                                                        | Purges the output                                                                                                   | Translates GROUPID to that specified in ADDMEM. If ADDMEM is not specified, uses the groupid received.                                                   |                                                                                                                                                                                                                                                                                            |                                                                                                                                                                                                             |
| security label (SECLS)                                                                                                                  | Purges the output                                                                                                   | Translates SECLABEL to that specified in ADDMEM. If ADDMEM is not specified, uses the security label received.                                           |                                                                                                                                                                                                                                                                                            |                                                                                                                                                                                                             |

Table 73. NODES Class Keywords, UACC, and SYSOUT Ownership when Execution Node is Not Defined to &RACLNDE (continued)

| Type of Check (keyword)                                                                                                                                                                                                                                                                                                                                      | UACC |      |        |                    |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|------|--------|--------------------|
|                                                                                                                                                                                                                                                                                                                                                              | NONE | READ | UPDATE | CONTROL or greater |
| <b>Notes:</b> <ol style="list-style-type: none"> <li>1. If the nodeid is specified in the RACFVARS profile named &amp;RACLNDE, the node is treated as a locally attached node and RACF verifies the supplied security information.</li> <li>2. Use the 'node.RUSER.userid' NODES class profile to provide command authority at your installation.</li> </ol> |      |      |        |                    |

## Translating Security Information

It might not be practical to maintain a RACF data base that contains all of the userids, groupids, and security labels that might enter your system through the network. However, you can translate inbound userids, groupids, or security labels into predefined values known to your system.

Use the ADDMEM operand on the RDEFINE or RALTER command to specify the translation values for inbound security information. For example, if you want all inbound work with a security label of VERYCONF to be translated to a security label of NOLOOKAT at your system, the security administrator would specify the following:

```
RDEFINE NODES *.SECL*.VERYCONF ADDMEM(NOLOOKAT) UACC(READ)
```

If you do not define profiles that translate inbound userids, then those userids must be defined in your RACF data base or the work will not pass RACF validation.

## Authorizing Inbound SYSOUT by Translating the Default Userid

Rather than translating the default userid to a universal userid, you can use the submitter's userid to translate the default to a unique userid that is valid for your system. To translate the default userid to a unique userid, ask your security administrator to:

1. Define a NODES profile that assigns the submitter's userid (&SUSER) to the inbound SYSOUT.
2. Define a NODES profile that translates the submitting userid (&SUSER) to a valid userid known to your node.

See *z/OS SecureWay Security Server RACF Security Administrator's Guide* for information about translating default userids.

## How JES2 Propagates Security Information

Propagation can occur across nodes in a network if the receiving node is at the MVS SP3.1.3 with JES2 SP3.1.3 level or later and RACF Version 1 Release 9 or later installed. When a node receives a job through a network, RACF determines who submitted the job. After determining the submitting userid, RACF can translate the submitting userid to a valid userid on this system if a profile on the receiving node specifies that the userid must be translated. RACF uses the submitting userid or its translation to supply any missing security information. Security information RACF propagates is:

- Userid
- Group
- Security label

If JES2 receives a request from an application or subsystem, JES2 propagates any security information provided by the application or subsystem to SAF.

## Defining Nodes as Local SYSOUT Sources

Your security administrator can have RACF treat SYSOUT received from other nodes the same as SYSOUT created by jobs running on local processors. To do this, the security administrator uses the &RACLNDE profile in the RACFVARS class to identify the nodes that you want RACF to consider as local SYSOUT sources. A node name defined to &RACLNDE either shares your RACF data base or is the value you are using to rename your node when you are changing node names. Defining remote nodes as local SYSOUT sources is useful if your node receives and processes SYSOUT as a back-up to another node.

**Note:** All local nodes, including the one on which the RACF data base resides, **must** be defined in the &RACLNDE profile in RACFVARS class.

## Authorizing Outbound Work

You can use RACF to control whether a specific node can receive work (jobs or SYSOUT).

For NJE, RACF ensures that the originator of outbound work is authorized to send the work to the target node. To activate protection for a node, ask your security administrator to activate the RACF WRITER class and define a profile for each node that you want to protect. You should provide your security administrator with the following information needed to define profiles:

- The name of your JES2 system.
- The list of users to be authorized or restricted from sending work to a specific node.
- The node name as specified in the JES2 initialization stream (where the specified node name is the ultimate destination of the output).
- The security label if you want to limit which security labels can appear on output that is sent to a particular destination.

RACF will check all data leaving your system for another node except data destined for another node your system received from a different node. This data RACF considers already validated and RACF protects the data with the default userid (????????) and the highest (SYSHIGH) security label possible while it resides on your spool. See “Authorizing the Use of Operator Commands” on page 364 for details on authorizing commands.

For information on sending output through the network see “Controlling Where Output Can Be Processed” on page 363.

## Controlling Access to Data that Resides on Spool

You can use RACF to provide security for your spool data including:

- SYSIN and SYSOUT data sets
- JESNEWS
- Trace data sets
- SYSLOG
- Spool offload data

The following sections identify what spool resources you can protect, and what information you must provide to your security administrator to control those resources.

## Controlling Access to SYSIN and SYSOUT

During job execution, JES2 creates data sets for a job's input (SYSIN) and output (SYSOUT). These data sets have profile names in the form:

localnodeid.userid.jobname.jobid.dsnumber.name

where:

**localnodeid**

The name of the node on which the SYSIN or SYSOUT data set currently resides. The localnodeid appears in the JES2 job log of every job.

**userid** The userid associated with the job. This is the userid RACF uses for validation purposes when the job runs.

**jobname**

The name that appears in the name field of the JOB statement.

**jobid** The job number JES2 assigned to the job. The jobid appears in notification messages and the JES2 job log of every job.

**dsnumber**

The unique data set number JES2 assigned to the spool data set. A “D” is the first character of this qualifier.

**name** The name of the data set specified in the DSN= parameter of the DD statement. This name cannot be JESYSMSG, JESJCLIN, JESJCL, or JESMSGGLG and follows the naming conventions for a temporary data set. See *z/OS MVS JCL Reference* for the temporary data set naming conventions. If the JCL did not specify DSN= on the DD statement that creates the spool data set, JES2 uses a question mark (?).

For example, if user MYUSER submits a job named MYJOB to run on NODEA, and JES2 assigns a jobid of JOB08237, and the value of DSN= for a SYSOUT data set is OUTPUT, the profile name for a SYSOUT data set created by this job could be:

NODEA.MYUSER.MYJOB.JOB08237.D0000112.OUTPUT

These data sets might exist after the job completes execution. Your RACF administrator can control access to these data sets by activating the JESSPOOL RACF class. If RACF is not active, JES2 always allows a job access to a SYSIN/SYSOUT data set the job creates. When RACF is active, RACF allows the userid (MYUSER in the preceding example) that creates a SYSIN/SYSOUT data set access to the data set, even though a profile might not exist for the data set. If any other users require access to a spool data set, the owner of the data set would have to define the data set profile (or a generic profile for the data set) and give access (through the RACF PERMIT command) to the users requiring the data.

**Note:** The data set name JES2 uses in its control blocks is the last 5 qualifiers used to build the RACF profile name.

## **SPOOL Browse access to SYSIN and SYSOUT**

Applications can use the SPOOL Browse interface to access data sets managed by JES2. SPOOL browse uses both the standard form of the JESSPOOL class profiles and a modified form for certain special system data sets. These special profiles are of the form:

localnodeid.userid.jobname.jobid.jes\_dsname

where:

**localnodeid**

The name of the node on which the SYSIN or SYSOUT data set currently resides. The localnodeid appears in the JES2 job log of every job.

**userid** The userid associated with the job. This is the userid RACF uses for validation purposes when the job runs.

**jobname**

The name that appears in the name field of the JOB statement.

**jobid** The job number JES2 assigned to the job. The jobid appears in notification messages and the JES2 job log of every job.

**jes\_dsname**

One of the following fixed names:

- JCL - This represents the jobs input JCL (with all SYSIN data sets)
- JESJCL - The JCL images data set as created by the conversion process
- JESMSGLOG - The JES2 job log data set
- JESYSMSG - The MVS SYSTEM messages data set

## Protecting JESNEWS

JESNEWS is an informational data set that prints after the header separator page of a job, if desired. Generally, this data set is of interest to all job submitters, so it is important that all users can read this information (UACC of READ).

The resource name for JESNEWS has the form:

```
nodeid.jesid.$JESNEWS.STCtaskid.Dnewslvl.JESNEWS
```

where:

**nodeid**

Is the name of the node that created the JESNEWS data set.

**jesid**

Is the userid associated with your JES2 system.

**taskid**

Is the name of the task that created the JESNEWS data set.

**newslvl**

Is the level of this copy of JESNEWS. The value of newslvl varies from 0000101 to 0065535.

The RACF profile name for JESNEWS on NODEB created by JOB01 is:

```
NODEB.SYSTEM.$JESNEWS.JOB01.D0000101.JESNEWS
```

To prevent unauthorized updating of JESNEWS, your RACF administrator must define another profile. This profile is in the RACF OPERCMDS class and any userids authorized to update JESNEWS must have CONTROL access to the profile. The JESNEWS update profile has the following form:

```
jesname.UPDATE.JESNEWS
```

If RACF is not active, JES2 requests authorization to update JESNEWS from the operator.

**Note:** If RACF and the SECLABEL class are active, RACF assigns the SECLABEL of the last job that updated JESNEWS to the JESNEWS profile. This could cause jobs with lower SECLABELs than the updating job to miss important information and RACF will record security violations for jobs accessing JESNEWS that did not previously occur. To make JESNEWS accessible to all users, the job that creates it should have a SECLABEL of SYSLOW and the data set profile should have a UACC of READ. If the SECLABEL is greater than SYSLOW, JESNEWS will not print in the output of any jobs submitted with a lower SECLABEL.



## Protecting Trace Data Sets

Trace data sets could contain information that compromises your installation's security (userids and passwords, for example). You protect these data sets in the RACF JESSPOOL class by defining a profile for the data sets and permitting only those userids that need access to the data sets. The profile for all trace data sets on NODE1 could be specified as:

```
NODE1.JES2.*.*.*.JESTRACE
```

The security administrator can then grant access to data sets that fit this profile to userids or groupids for the system support group(s). If you also use security labels for controlling your data, the trace data set(s) should have the highest (SYSHIGH) security label in your installation.

## Protecting SYSLOG

Your security policy might require that you protect SYSLOG because it is the record of your systems daily activities.

To control SYSLOG, your security administrator defines a RACF JESSPOOL profile for the data set, an appropriate universal access, and then grants access to the userids or groupids that need a different access. NODEB's SYSLOG profile could look like this:

```
NODEB.+MASTER+.*.*.*.?
```

If you also use security labels for controlling your data, the SYSLOG data set(s) should have the highest (SYSHIGH) security label in your installation.

## Protecting Spool Offload Data Sets

You should protect offloaded information by defining the offload data set to RACF with no (NONE) universal access authority. If you have security labels active, you should assign the offload data a SECLABEL of SYSHIGH, to prevent unauthorized access.

**Offload:** When you offload data from the spool to another device, JES2 copies the security information for the data to the offload job and data set headers. No validation is made of the security information written to the offload data set. JES2 calls RACF to ensure the operator starting the offload operation has sufficient authority to issue the command to start the offload.

During the offload process, JES2 calls RACF (using the WRITER class) to ensure the owner of the SYSOUT data set has access to the offload device by checking the security information associated with the data against the device's profile in the RACF WRITER class. The offload device profile for offload SYSOUT transmitter 1 would be:

```
jesx.LOCAL.OFF1.ST
```

During spool offload, jobs are not checked for access to the device.

**Reload:** When JES2 reloads the information from an offload data set, it performs any security validation necessary (similar to reading a job into the system or receiving a network SYSOUT data set) before writing the data to spool by checking the RACF JESJOBS class for reloaded jobs and the RACF NODES class. When RACF performs the NODES class check, if the node associated with the data is in &RACLNDE, RACF accepts the data.

The following profiles for the JESINPUT class apply to spool reload:

OFFn.JR      for jobs  
OFFn.SR      for SYSOUT

As with offload, JES2 calls RACF to ensure the operator starting the reload operation has sufficient authority to issue the commands.

**Attention:** When using security labels, data offloaded from a JES2 SP3.1.3 or later member reloaded to a pre-SP3.1.3 member could cause a security exposure because the pre-SP3.1.3 member cannot validate security labels.

When reloading a data set that was offloaded on this node, the name of the node must be defined in &RACLNDE.

## Controlling Where Output Can Be Processed

JES2 normally processes output on any device that matches the output's selection criteria. You might, however, wish to control the specific devices certain users can access. For example, you might want the users who process your payroll to be the only users of a particular printer.

By defining the device to RACF (as a profile in RACF class WRITER), you can limit access to that device to a user or group of users. When a defined device selects a piece of output for processing, JES2 passes an authorization request to SAF; access to the device depends on the response JES2 receives. RACF profile names for devices have the following formats:

For local devices,

jesname.LOCAL.devicename

For RJE devices,

jesname.RJE.devicename

**Note:** RJE printers and punches are specified as Rnnnn.PRM and Rnnnn.PUM.  
For data destined to a node,

jesname.NJE.nodename

where:

**jesname**

The JES2 system that defines the node

**devicename**

The name of the JES2 initialization statement that defines this device.

**nodename**

The name of the NODE(nnnn) statement that defines the node.

Your security administrator would then grant access to the devices to the userids and groupids you have identified.

Also, if security label verification is active, RACF ensures that the device can write this data depending on the security label specified. If your RACF options require the security label of the device to be equal to or greater than the security label of the output, the device will not be able to process the output.

If a device cannot select output because the device does not have sufficient access to that output, the output remains on the output queue until you:

- Change the security attributes of the device; you must then stop and restart that device for the security attributes to take affect.
- Authorize the userid associated with the output to the device.

- Change the work selection criteria of the output so that a device with the appropriate security attributes can select the output.

RACF also allows your installation to print security labels on printed output that PSF-managed printers process. See *z/OS SecureWay Security Server RACF Security Administrator's Guide* for information about printing security labels on job output using RACF. Also, see *z/OS MVS JCL User's Guide* for information about using the OUTPUT JCL statement to print security labels.

### Controlling External Writers

An external writer is a started task used to process output. Because the external writer is a started task, it has a userid associated with it. You process output with an external writer by naming the writer on the DD statement (or OUTPUT JCL statement) that defines the output as follows:

```
//MYOUTPUT DD SYSOUT=(A,XTWTR)
```

For the writer to be able to process that output, the writer's userid must be in an access list that permits the writer's userid to access the SYSOUT data set. The minimum access required for external writers is ALTER. The writer's userid is the userid specified in the started procedure table for the writer task. Alternately, you can define external writers with the trusted attribute in the started procedures table. However, the trusted attribute might be contrary to your installation's policy and allows the external writer access to data you might not want it to process.

Also, if your policy requires security labels, the security label associated with the external writer must be equal to or greater than the security label associated with the SYSOUT.

## Authorizing the Use of Operator Commands

Your installation can require that only certain operators issue certain JES2 commands. There could also be a requirement to restrict commands coming in from RJE workstations, NJE nodes, or any other device.

To control commands, you should review the commands and your installation's security policy with your RACF administrator and determine:

- The list of commands you need to control
- The command profile names
- The appropriate authority level for any restricted commands
- The authority level your policy requires to issue a particular command
- the list of users or groups authorized to issue each command.

The command resource names have the format:

```
jesname.command[.qualifier]
```

where:

**jesname**

The name of the JES2 system requesting the command validation.

**command**

The name of the command.

**qualifier**

The type of object the command specifies. (For example, JOB or SYS.)

Table 75 on page 366 contains a list of commands, a sample resource name for each command, and the minimum required authority level for each command. (If you give an operator access to a command with a lower authority than the authority

in the table, RACF will not allow the operator to issue the command.) The authority levels give you a means of controlling commands that can affect your installation's processing.

Ensure that your RACF administrator activates the OPERCMDS class and defines each command profile to that class. In order to minimize the number of definitions, commands should be defined with generic profile name unless you are restricting specific commands. Supply your RACF administrator with a generic name that covers a group of commands and then group restricted commands in that group with a more specific name. For example,

jesx.\*

would define all commands as a group. Then,

jesx.START.\*

defines all start commands.

The first definition, jesx.\*, could restrict a group of operators to only the commands that need READ authority. Then your RACF administrator would define any operators who would need access to all the start commands with CONTROL authority. The operators with CONTROL authority are able to issue all commands based on the RACF authority hierarchy shown in Table 74 on page 365.

*Table 74. RACF Command Authority Hierarchy. The following assumes a specific profile does not exist that would prevent the operator from issuing a command.*

| Access Level | Commands Operator Can Issue                |
|--------------|--------------------------------------------|
| CONTROL      | All commands                               |
| UPDATE       | All commands specified with UPDATE or READ |
| READ         | Only commands specified with READ          |

If you need to restrict commands to specific consoles, your RACF administrator should define an operator's access conditional to the console from which the operator enters the command. For more information on conditional access, see *z/OS SecureWay Security Server RACF Security Administrator's Guide*.

If you expect commands to enter your system from local readers, you **must** have an operator issue the \$S RDRx command rather than have JES2 start the reader. This ensures RACF has a specific userid to use when checking command authorization.

To control the commands entering from RJE workstations your security administrator must do the following:

- Define the RJE workstation profile in the RACF FACILITY class.
- Define the RJE workstation as a valid RACF userid using the remote name.
- Permit the RJE userid to the command profiles the node can issue.

The FACILITY class profile for RMT(1) has the form:

RJE.RMT1

The userid your administrator would define to RACF is RMT1.

Your administrator would use a similar process to define an NJE node in order to control commands.

- Define the node to the RACF NODES class

- Define the node to the RACF FACILITY class
- Define the node as a RACF userid
- Permit the node's userid to the command profiles the node can issue

The FACILITY class profile for node 1 named HYDEPARK is:

```
NJE.HYDEPARK
```

To control access to commands from other NJE nodes, use the following NODES class profile:

```
,RUSER.
```

Your security policy can require auditing of all commands issued, even if they are not valid on your system. You can audit commands that might be unknown to JES2 by defining a profile called JESx.UNKNOWN with a UACC of NONE and an AUDIT value of ALL. JES2 validates all unknown commands with the JESx.UNKNOWN profile.

If you need a finer level of control over your commands (for example, you want only certain operators to change the routing of a printer), you should use JES2 Exit 36. See *z/OS JES2 Installation Exits* for information about Exit 36.

*Table 75. JES2 Commands with Profile Names and Minimum Required Authority*

| JES2 command   | Example Profile Name   | Minimum Required User Access Level |
|----------------|------------------------|------------------------------------|
| \$A A          | jesx.MODIFYRELEASE.JOB | UPDATE                             |
| \$A J          | jesx.MODIFYRELEASE.BAT | UPDATE                             |
| \$A JOBQ       | jesx.MODIFYRELEASE.JST | UPDATE                             |
| \$A S          | jesx.MODIFYRELEASE.STC | UPDATE                             |
| \$A T          | jesx.MODIFYRELEASE.TSU | UPDATE                             |
| \$ADD APPL     | jesx.ADD.APPL          | CONTROL                            |
| \$ADD CONNECT  | jesx.ADD.CONNECT       | CONTROL                            |
| \$ADD DESTID   | jesx.ADD.DESTID        | CONTROL                            |
| \$ADD FSS      | jesx.ADD.FSS           | CONTROL                            |
| \$ADD LINE     | jesx.ADD.LINE          | CONTROL                            |
| \$ADD LOGON    | jesx.ADD.LOGON         | CONTROL                            |
| \$ADD PRTnnnn  | jesx.ADD.DEV           | UPDATE                             |
| \$ADD REDIRECT | jesx.ADD.REDIRECT      | CONTROL                            |
| \$ADD RMT      | jesx.ADD.RMT           | CONTROL                            |
| \$B device     | jesx.BACKSP.DEV        | UPDATE                             |
| \$C A**        | jesx.CANCEL.AUTOCMD    | *****                              |
| \$C J          | jesx.CANCEL.BAT        | UPDATE                             |
| \$C Lx.yy      | jesx.CANCEL.DEV        | UPDATE                             |
| \$C O J        | jesx.CANCEL.BATOUT     | UPDATE                             |
| \$C O JOBQ     | jesx.CANCEL.JSTOUT     | UPDATE                             |
| \$C O S        | jesx.CANCEL.STCOUT     | UPDATE                             |
| \$C O T        | jesx.CANCEL.TSUOUT     | UPDATE                             |
| \$C S          | jesx.CANCEL.STC        | UPDATE                             |
| \$C T          | jesx.CANCEL.TSU        | UPDATE                             |

Table 75. JES2 Commands with Profile Names and Minimum Required Authority (continued)

| JES2 command      | Example Profile Name   | Minimum Required User Access Level |
|-------------------|------------------------|------------------------------------|
| \$C device        | jesx.CANCEL.DEV        | UPDATE                             |
| \$C OFFn.JR       | jesx.CANCEL.DEV        | UPDATE                             |
| \$C OFFn.JT       | jesx.CANCEL.DEV        | UPDATE                             |
| \$C OFFn.SR       | jesx.CANCEL.DEV        | UPDATE                             |
| \$C OFFn.ST       | jesx.CANCEL.DEV        | UPDATE                             |
| \$D A             | jesx.DISPLAY.JOB       | READ                               |
| \$D ACTIVATE      | jesx.DISPLAY.ACTIVATE  | READ                               |
| \$D ACTRMT        | jesx.DISPLAY.ACTRMT    | READ                               |
| \$D CKPTDEF       | jesx.DISPLAY.CKPTDEF   | READ                               |
| \$D CONDEF        | jesx.DISPLAY.CONDEF    | READ                               |
| \$D CONNECT       | jesx.DISPLAY.CONNECT   | READ                               |
| \$D DESTDEF       | jesx.DISPLAY.DESTDEF   | READ                               |
| \$D DESTid        | jesx.DISPLAY.DESTID    | READ                               |
| \$D F             | jesx.DISPLAY.QUE       | READ                               |
| \$D I             | jesx.DISPLAY.INITIATOR | READ                               |
| \$D J             | jesx.DISPLAY.BAT       | READ                               |
| \$D JOBCLASS      | jesx.DISPLAY.JOBCLASS  | READ                               |
| \$D JOBQ          | jesx.DISPLAY.JST       | READ                               |
| \$D L(nnnn).JR(n) | jesx.DISPLAY.L         | READ                               |
| \$D L(nnnn).JT(n) | jesx.DISPLAY.L         | READ                               |
| \$D L(nnnn).SR(n) | jesx.DISPLAY.L         | READ                               |
| \$D L(nnnn).ST(n) | jesx.DISPLAY.L         | READ                               |
| \$D LINE          | jesx.DISPLAY.LINE      | READ                               |
| \$D LOADmod       | jesx.DISPLAY.LOADMED   | READ                               |
| \$D M             | jesx.SEND.MESSAGE      | READ                               |
| \$D MASDEF        | jesx.DISPLAY.MASDEF    | READ                               |
| \$D MEMBer        | jesx.DISPLAY.SYS       | READ                               |
| \$D MODULE        | jesx.DISPLAY.MODULE    | READ                               |
| \$D N             | jesx.DISPLAY.JOB       | READ                               |
| \$D NJEDEF        | jesx.DISPLAY.NJEDEF    | READ                               |
| \$D NODE          | jesx.DISPLAY.NODE      | READ                               |
| \$D O J           | jesx.DISPLAY.BATOUT    | READ                               |
| \$D O JOBQ        | jesx.DISPLAY.JSTOUT    | READ                               |
| \$D OPTSDEF       | jesx.DISPLAY.OPTSDEF   | READ                               |
| \$D O S           | jesx.DISPLAY.STCOUT    | READ                               |
| \$D O T           | jesx.DISPLAY.TSUOUT    | READ                               |
| \$D PATH          | jesx.DISPLAY.PATH      | READ                               |
| \$D PCE           | jesx.DISPLAY.PCE       | READ                               |

Table 75. JES2 Commands with Profile Names and Minimum Required Authority (continued)

| JES2 command          | Example Profile Name    | Minimum Required User Access Level |
|-----------------------|-------------------------|------------------------------------|
| \$D PRT               | jesx.DISPLAY.DEV        | READ                               |
| \$D PRTnnnn           | jesx.DISPLAY.DEV        | READ                               |
| \$D Q                 | jesx.DISPLAY.JOB        | READ                               |
| \$D REBLD             | jesx.DISPLAY.REBLD      | READ                               |
| \$D RDI               | jesx.DISPLAY.RDI        | READ                               |
| \$D RDRnn             | jesx.DISPLAY.DEV        | READ                               |
| \$D Rnnnn.CON         | jesx.DISPLAY.DEV        | READ                               |
| \$D Rnnnn.PRm         | jesx.DISPLAY.DEV        | READ                               |
| \$D Rnnnn.PUm         | jesx.DISPLAY.DEV        | READ                               |
| \$D Rnnnn.RDm         | jesx.DISPLAY.DEV        | READ                               |
| \$D REDIRect          | jesx.DISPLAY.REDIRECT   | READ                               |
| \$D S                 | jesx.DISPLAY.STC        | READ                               |
| \$D SPOOL             | jesx.DISPLAY.SPOOL      | READ                               |
| \$D SPOOLDEF          | jesx.DISPLAY.SPOOLDEF   | READ                               |
| \$D SSI               | jesx.DISPLAY.SSI        | READ                               |
| \$D SUBNET            | jesx.DISPLAY.SUBNET     | READ                               |
| \$D T                 | jesx.DISPLAY.TSU        | READ                               |
| \$D TRACE(x)          | jesx.DISPLAY.TRACE      | READ                               |
| \$D U                 | jesx.DISPLAY.DEV        | READ                               |
| \$D init stmt         | jesx.DISPLAY.initstmt   | READ                               |
| \$D PUNnn             | jesx.DISPLAY.DEV        | READ                               |
| \$DEL CONNECT         | jesx.DEL.CONNECT        | CONTROL                            |
| \$DEL DESTID          | jesx.DEL.DESTID         | CONTROL                            |
| \$E CKPTLOCK          | jesx.RESTART.SYS        | CONTROL                            |
| \$E J                 | jesx.RESTART.BAT        | CONTROL                            |
| \$E LINE(x)           | jesx.RESTART.LINE       | CONTROL                            |
| \$E LOGON(x)          | jesx.RESTART.LOGON      | CONTROL                            |
| \$E MEMBER()          | jesx.RESTART.SYS        | CONTROL                            |
| \$E OFFn.JT           | jesx.RESTART.DEV        | UPDATE                             |
| \$E OFFn.ST           | jesx.RESTART.DEV        | UPDATE                             |
| \$E device            | jesx.RESTART.DEV        | UPDATE                             |
| \$F device            | jesx.FORWARD.DEV        | UPDATE                             |
| \$G A                 | jesx.GMODIFYRELEASE.JOB | UPDATE                             |
| \$G C                 | jesx.GCANCEL.JOB        | UPDATE                             |
| \$G D                 | jesx.GDISPLAY.JOB       | READ                               |
| \$G H                 | jesx.GMODIFYHOLD.JOB    | UPDATE                             |
| \$G R                 | jesx.GROUTE.JOBOUT      | UPDATE                             |
| \$G R (for execution) | jesx.GROUTE.JOBOUT      | UPDATE                             |



Table 75. JES2 Commands with Profile Names and Minimum Required Authority (continued)

| JES2 command | Example Profile Name | Minimum Required User Access Level |
|--------------|----------------------|------------------------------------|
| \$H A        | jesx.MODIFYHOLD.JOB  | UPDATE                             |
| \$H J        | jesx.MODIFYHOLD.BAT  | UPDATE                             |
| \$H JOBQ     | jesx.MODIFYHOLD.JST  | UPDATE                             |
| \$H S        | jesx.MODIFYHOLD.STC  | UPDATE                             |
| \$H T        | jesx.MODIFYHOLD.TSU  | UPDATE                             |
| \$I device   | jesx.INTERRUPT.DEV   | UPDATE                             |
| \$L J        | jesx.DISPLAY.BATOUT  | READ                               |
| \$L JOBQ     | jesx.DISPLAY.JSTOUT  | READ                               |
| \$L S        | jesx.DISPLAY.STCOUT  | READ                               |
| \$L T        | jesx.DISPLAY.TSUOUT  | READ                               |
| \$M          | jesx.MSEND.CMD       | READ                               |
| \$N          | jesx.NSEND.CMD       | READ                               |
| \$N device   | jesx.REPEAT.DEV      | UPDATE                             |
| \$O J        | jesx.RELEASE.BATOUT  | UPDATE                             |
| \$O JOBQ     | jesx.RELEASE.JSTOUT  | UPDATE                             |
| \$O S        | jesx.RELEASE.STCOUT  | UPDATE                             |
| \$O T        | jesx.RELEASE.TSUOUT  | UPDATE                             |
| \$P          | jesx.STOP.SYS        | CONTROL                            |
| \$P I        | jesx.STOP.INITIATOR  | CONTROL                            |
| \$P JES2     | jesx.STOP.SYS        | CONTROL                            |
| \$P JOBQ     | jesx.STOP.JST        | UPDATE                             |
| \$P LINE(x)  | jesx.STOP.LINE       | CONTROL                            |
| \$P LOGON(x) | jesx.STOP.LOGON      | CONTROL                            |
| \$P O J      | jesx.STOP.BATOUT     | UPDATE                             |
| \$P O JOBQ   | jesx.STOP.JSTOUT     | UPDATE                             |
| \$P O S      | jesx.STOP.STCOUT     | UPDATE                             |
| \$P O T      | jesx.STOP.TSUOUT     | UPDATE                             |
| \$P OFFn.JR  | jesx.STOP.DEV        | UPDATE                             |
| \$P OFFn.JT  | jesx.STOP.DEV        | UPDATE                             |
| \$P OFFn.SR  | jesx.STOP.DEV        | UPDATE                             |
| \$P OFFn.ST  | jesx.STOP.DEV        | UPDATE                             |
| \$P OFFLOADn | jesx.STOP.DEV        | UPDATE                             |
| \$P RMT(x)   | jesx.STOP.RMT        | CONTROL                            |
| \$P S        | jesx.STOP.STC        | UPDATE                             |
| \$P SPOOL    | jesx.STOP.SPOOL      | CONTROL                            |
| \$P T        | jesx.STOP.TSU        | UPDATE                             |
| \$P TRACE(x) | jesx.STOP.TRACE      | CONTROL                            |
| \$P XEQ      | jesx.STOP.SYS        | CONTROL                            |

Table 75. JES2 Commands with Profile Names and Minimum Required Authority (continued)

| JES2 command     | Example Profile Name | Minimum Required User Access Level |
|------------------|----------------------|------------------------------------|
| \$P device       | jesx.STOP.DEV        | UPDATE                             |
| \$PO JOBQ        | jesx.STOP.JSTOUT     | UPDATE                             |
| \$PO JOB         | jesx.STOP.BATOUT     | UPDATE                             |
| \$PO STC         | jesx.STOP.STCOUT     | UPDATE                             |
| \$PO TSU         | jesx.STOP.TSUOUT     | UPDATE                             |
| \$R ALL          | jesx.ROUTE.JOBOUT    | UPDATE                             |
| \$R PRT          | jesx.ROUTE.JOBOUT    | UPDATE                             |
| \$R PUN          | jesx.ROUTE.JOBOUT    | UPDATE                             |
| \$R XEQ          | jesx.ROUTE.JOBOUT    | UPDATE                             |
| \$S              | jesx.START.SYS       | CONTROL                            |
| \$S A            | jesx.START.AUTOCMD   | CONTROL                            |
| \$S I            | jesx.START.INITIATOR | CONTROL                            |
| \$S J            | jesx.START.BAT       | UPDATE                             |
| \$S LINE(x)      | jesx.START.LINE      | CONTROL                            |
| \$S LOGON(x)     | jesx.START.LOGON     | CONTROL                            |
| \$S N            | jesx.START.NET       | CONTROL                            |
| \$S OFFn.JR      | jesx.START.DEV       | UPDATE                             |
| \$S OFFn.JT      | jesx.START.DEV       | UPDATE                             |
| \$S OFFn.SR      | jesx.START.DEV       | UPDATE                             |
| \$S OFFn.ST      | jesx.START.DEV       | UPDATE                             |
| \$S OFFLOADn     | jesx.START.DEV       | UPDATE                             |
| \$S RMT(x)       | jesx.START.RMT       | CONTROL                            |
| \$S SPOOL        | jesx.START.SPOOL     | CONTROL                            |
| \$S TRACE(x)     | jesx.START.TRACE     | CONTROL                            |
| \$S XEQ          | jesx.START.SYS       | CONTROL                            |
| \$S device       | jesx.START.DEV       | UPDATE                             |
| \$T A(CREATE)    | jesx.MODIFY.AUTOCMD  | READ                               |
| \$T A(OWNER)     | jesx.MODIFY.AUTOCMD  | READ                               |
| \$T A(NOT OWNER) | jesx.MODIFY.AUTOCMD  | CONTROL                            |
| \$T APPL         | jesx.MODIFY.APPL     | CONTROL                            |
| \$T BUFDEF       | jesx.MODIFY.BUFDEF   | CONTROL                            |
| \$T CKPTDEF      | jesx.MODIFY.CKPTDEF  | CONTROL                            |
| \$T CONDEF       | jesx.MODIFY.CONDEF   | CONTROL                            |
| \$T CONNECT      | jesx.MODIFY.CONNECT  | CONTROL                            |
| \$T DEBUG        | jesx.MODIFY.DEBUG    | CONTROL                            |
| \$T DESTDEF      | jesx.MODIFY.DESTDEF  | CONTROL                            |
| \$T DESTid       | jesx.MODIFY.DESTID   | CONTROL                            |
| \$T ESTBYTE      | jesx.MODIFY.ESTBYTE  | CONTROL                            |

Table 75. JES2 Commands with Profile Names and Minimum Required Authority (continued)

| JES2 command  | Example Profile Name  | Minimum Required User Access Level |
|---------------|-----------------------|------------------------------------|
| \$T ESTIME    | jesx.MODIFY.ETIME     | CONTROL                            |
| \$T ESTLNCT   | jesx.MODIFY.ESTLNCT   | CONTROL                            |
| \$T ESTPAGE   | jesx.MODIFY.ESTPAGE   | CONTROL                            |
| \$T ESTPUN    | jesx.MODIFY.ESTPUN    | CONTROL                            |
| \$T EXIT      | jesx.MODIFY.EXIT      | CONTROL                            |
| \$T FSS       | jesx.MODIFY.FSS       | CONTROL                            |
| \$T I         | jesx.MODIFY.INITIATOR | CONTROL                            |
| \$T INTRDR    | jesx.MODIFY.INTRDR    | CONTROL                            |
| \$T J         | jesx.MODIFY.BAT       | UPDATE                             |
| \$T JOBCLASS  | jesx.MODIFY.JOBCLASS  | CONTROL                            |
| \$T JOBDEF    | jesx.MODIFY.JOBDEF    | CONTROL                            |
| \$T JOBPRTY   | jesx.MODIFY.JOBPRTY   | CONTROL                            |
| \$T JOBQ      | jesx.MODIFY.JST       | UPDATE                             |
| \$T LINE      | jesx.MODIFY.LINE      | CONTROL                            |
| \$T LOGON     | jesx.MODIFY.LOGON     | CONTROL                            |
| \$T MASDEF    | jesx.MODIFY.MASDEF    | CONTROL                            |
| \$T MEMBER(x) | jesx.MODIFY.SYS       | CONTROL                            |
| \$T NODE      | jesx.MODIFY.NODE      | CONTROL                            |
| \$T NJEDEF    | jesx.MODIFY.NJEDEF    | CONTROL                            |
| \$T NUM       | jesx.MODIFY.NUM       | CONTROL                            |
| \$T O J       | jesx.MODIFY.BATOUT    | UPDATE                             |
| \$T O JOBQ    | jesx.MODIFY.JSTOUT    | UPDATE                             |
| \$T O S       | jesx.MODIFY.STCOUT    | UPDATE                             |
| \$T O T       | jesx.MODIFY.TSUOUT    | UPDATE                             |
| \$T OFFx.yy   | jesx.MODIFY.OFF       | CONTROL                            |
| \$T OFFLOADx  | jesx.MODIFY.OFFLOAD   | CONTROL                            |
| \$T OUTCLASS  | jesx.MODIFY.OUTCLASS  | CONTROL                            |
| \$T OUTDEF    | jesx.MODIFY.OUTDEF    | CONTROL                            |
| \$T OUTPRTY   | jesx.MODIFY.OUTPRTY   | CONTROL                            |
| \$T PCE       | jesx.MODIFY.PCE       | CONTROL                            |
| \$T PRINTDEF  | jesx.MODIFY.PRINTDEF  | CONTROL                            |
| \$T RECVopts  | jesx.MODIFY.RECVOPTS  | CONTROL                            |
| \$T REDIRect  | jesx.MODIFY.REDIRECT  | CONTROL                            |
| \$T RMT       | jesx.MODIFY.RMT       | CONTROL                            |
| \$T S         | jesx.MODIFY.STC       | UPDATE                             |
| \$T SMFDEF    | jesx.MODIFY.SMFDEF    | CONTROL                            |
| \$T SPOOLDEF  | jesx.MODIFY.SPOOLDEF  | CONTROL                            |
| \$T SPOOL     | jesx.MODIFY.SPOOL     | CONTROL                            |

Table 75. JES2 Commands with Profile Names and Minimum Required Authority (continued)

| JES2 command  | Example Profile Name  | Minimum Required User Access Level |
|---------------|-----------------------|------------------------------------|
| \$T SSI       | jesx.MODIFY.SSI       | CONTROL                            |
| \$T STCCCLASS | jesx.MODIFY.STCCCLASS | CONTROL                            |
| \$T TPDEF     | jesx.MODIFY.TPDEF     | CONTROL                            |
| \$T TRACEDEF  | jesx.MODIFY.TRACEDEF  | CONTROL                            |
| \$T T         | jesx.MODIFY.TSU       | UPDATE                             |
| \$T device    | jesx.MODIFY.DEV       | UPDATE                             |
| \$T init stmt | jesx.MODIFY.init stmt | CONTROL                            |
| \$T TSUCLASS  | jesx.MODIFY.TSUCLASS  | CONTROL                            |
| \$VS*         | jesx.VS               | CONTROL                            |
| \$Z A         | jesx.HALT.AUTOCMD     | CONTROL                            |
| \$Z I         | jesx.HALT.INITIATOR   | CONTROL                            |
| \$Z OFFLOADn  | jesx.HALT.DEV         | UPDATE                             |
| \$Z SPOOL     | jesx.HALT.SPOOL       | CONTROL                            |
| \$Z device    | jesx.HALT.DEV         | UPDATE                             |
| \$ZAPJOB      | jesx.ZAP.JOB          | CONTROL                            |

### Considerations for Automatic Commands

Automatic commands have the same types of controls as other commands. Profiles exist for the specific automatic commands (\$TA, \$CA, \$ZA, \$HA) but there are other things you must consider when issuing the automatic commands.

- The issuer of the automatic command must have the appropriate authority for the automatic command and all commands the automatic command issues. JES2 passes the security information of the originator of the automatic command with all the commands issued by the automatic command. RACF uses the originator's userid when deciding if the user can issue any particular command.
- To update an automatic command, your userid must either be the userid that originally issued the automatic command with READ access or have CONTROL access to automatic commands. You should consider giving CONTROL access to automatic commands to a limited number of operators who need to change the automatic commands on a regular basis.

---

## Using JES2 to Provide Security

JES2 has a number of JES2 initialization statement parameters and installation exits that you can use to protect JES2. Some of the resources that you can protect using JES2-provided facilities include:

- NJE communication lines
- RJE communication lines
- Remote workstation SIGNON/LOGON
- VTAM sessions
- Commands

## JES2 Initialization Statements

You can use JES2 initialization statements to control:

- Access to your system by:

- RJE lines and workstations [LINE(nnnn) and RMT(nnnn)]
- NJE lines and nodes [LINE(nnnn) and NODE(nnnn)]
- JES2 access to VTAM [LOGON(n)]
- Job transmission or forwarding to:
  - Another node with encrypted passwords [NODE(nnnn)]
  - Spool offload devices
- Output to:
  - Local devices
  - Remote workstation devices
  - Other nodes [NODE(nnnn)]
  - Spool offload devices [OFFLOAD(n)]
- Operator commands entering the system:
  - Through internal readers (INTRDR)
  - Through readers [RDR(nn)]
  - From other nodes [NODE(nnnn)]
  - From jobs, started tasks, or a TSO/E session [JOBCLASS(v)]

when RACF is not active or installed.

Table 76 shows the JES2 initialization statements and parameters that deal with security, the resources they affect, and a brief description of each parameter. For detailed information about each parameter, see *z/OS JES2 Initialization and Tuning Reference*.

Table 76. JES2 Security-Related Initialization Statements

| Statement   | Parameter  | Resource Affected       | Parameter Description                                                                                                                                                                                                                  |
|-------------|------------|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DEBUG       | SECURITY=  | device access           | Specifies whether JES2 provides additional RACF security logging to include warnings for JES2 output work selection for JES2 devices and external writer (XWTR) requests and SYSOUT Application Programming Interface (SAPI) requests. |
| INTRDR      | AUTH=*     | commands                | Determines the types of commands accepted from any internal reader.                                                                                                                                                                    |
| JOBCLASS(n) | AUTH= *    | commands                | Determines the group of MVS commands accepted from a particular job class, started tasks, or TSO/E sessions.                                                                                                                           |
|             | COMMAND= * | commands                | Defines the action the system takes when encountering an MVS command in the job stream.                                                                                                                                                |
| LINE(nnnn)  | PASSWORD=  | system access from line | Restricts access to the system from this line to workstations specifying the proper password.                                                                                                                                          |
| LOGON(n)    | PASSWORD=  | VTAM access             | Restricts access by JES2 to VTAM.                                                                                                                                                                                                      |

Table 76. JES2 Security-Related Initialization Statements (continued)

| Statement                                                                | Parameter   | Resource Affected                   | Parameter Description                                                                           |
|--------------------------------------------------------------------------|-------------|-------------------------------------|-------------------------------------------------------------------------------------------------|
| NODE(nnnn)                                                               | AUTH= *     | commands                            | Defines the command authority another node has on your system.                                  |
|                                                                          | PASSWORD=   | system access from node             | Restricts access to the system from the node this statement defines.                            |
|                                                                          | PENCRYPT=   | password encryption                 | Enables encryption of passwords sent with data and jobs to this node.                           |
|                                                                          | RECEIVE=    | data                                | Defines the type of data your system can receive from an adjacent node.                         |
|                                                                          | TRANSMIT=   | data                                | Defines the type of data your system can transmit to an adjacent node.                          |
| OFFLOAD(n)                                                               | PROTECT=    | spool offload data set              | Specifies whether the spool offload data set needs RACF protection.                             |
| RDR(nn)                                                                  | AUTH= *     | commands                            | Determines the types of commands accepted from a reader.                                        |
| RMT(nnnn)                                                                | PASSWORD= * | system access from remote terminals | Restricts access to the system from this remote to workstations specifying the proper password. |
| * This parameter takes affect only when RACF is not active or installed. |             |                                     |                                                                                                 |

## JES2 Security Exit Points

You can enhance standard JES2 security by performing your own validation at certain exit points. These exits are located at strategic places in the processing and using existing information, you can make decisions about access to certain resources. Table 77 lists the JES2 exits related to security and a brief description of how you could use them.

Table 77. Security-Related Exits

| Exit | Exit Name                           | Description                                                                                                                                       |
|------|-------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|
| 2    | JOB Statement Scan                  | Perform password validation or restrict job names to certain users.                                                                               |
| 3    | JOB Statement Accounting Field Scan | Validate the account number on the JOB statement.                                                                                                 |
| 4    | JCL and JES2 Control Statement Scan | Restrict resources a job uses based on information in the JCL or JES2 Control statements. Inspect and validate commands imbedded in a job stream. |
| 5    | JES2 Command Preprocessor           | Restrict commands processed by JES2. Allow or disallow commands based on the parameters specified.                                                |
| 6    | Converter/Interpreter Text Scan     | Restrict resources a job uses based on information in the JCL.                                                                                    |

Table 77. Security-Related Exits (continued)

| Exit | Exit Name                                                               | Description                                                                      |
|------|-------------------------------------------------------------------------|----------------------------------------------------------------------------------|
| 13   | TSO/E Interactive Data Transmission Facility Screening and Notification | Restrict data received from nodes through the TSO/E RECEIVE command.             |
| 17   | BSC RJE SIGN-ON/SIGN-OFF                                                | Control the BSC RJE devices that access your system.                             |
| 18   | SNA RJE LOGON/LOGOFF                                                    | Control the SNA RJE devices that access your system.                             |
| 20   | END OF JOB INPUT                                                        | Perform a final check of a job's attributes after JES2 processes all the input.  |
| 22   | CANCEL/STATUS                                                           | Restrict use of the TSO/E CANCEL and STATUS commands.                            |
| 30   | OPEN (and RESTART) of SSI Data Sets and Internal Readers                | Control access to data sets residing on spool. Restrict use of internal readers. |
| 31   | Allocation of SSI Data Sets and Internal Readers                        | Control access to SSI data sets or internal readers.                             |
| 32   | SSI Job Selection                                                       | Control which jobs JES2 selects for execution.                                   |
| 33   | SSI Data Set Close                                                      | Validate characteristics and destination of subsystem data sets.                 |
| 34   | SSI Data Set Unallocation                                               | Validate characteristics and destination of subsystem data sets.                 |
| 36   | Pre-Security Authorization Call                                         | Modify the information passed to SAF.                                            |
| 37   | Post-Security Authorization Call                                        | Perform other security checks before granting access to a resource.              |
| 38   | TSO/E RECEIVE Data Set Disposition                                      | Change the default processing for a data set that the user can never receive.    |
| 39   | NJE SYSOUT Data Set Disposition                                         | Change the default processing for an NJE SYSOUT data set that failed validation. |

See *z/OS JES2 Installation Exits* for details on implementing these exits.

## Multiple Levels of a Security Product in a MAS

JES2 security support assumes that the same level of the security product is installed on all members of a MAS and that the security product's data base is the same on all members. Unexpected security failures and inconsistent audit records might occur if this is not the case.

For example, if the security product on member 1 requires SECLABELs and the security product on member 2 does not support SECLABELs, then a job submitted on member 2 but run on member 1 can fail because it has no SECLABEL. Security failures can also occur attempting to access from member 1, a job submitted on member 2 or SYSOUT created on member 2. Accesses that can fail include the JESSPOOL call made when a SPOOL data set is purged. The data set will be purged, but a security violation audit record and message might be generated.



Complete audit records might not be available in this environment. Audit records will only be created by systems with security products that support the appropriate classes. Access from other systems will not be audited.

For these reasons, it is recommended that classes/profiles related to JES2 should not be activated until all members have security products capable of supporting those classes/profiles. Also, those classes should be activated on all members at the same time.

Special consideration must be given to MASes in which one member has a security product and the other does not. Information placed in TOKENs by SAF on a system with no security product has not been authenticated. The security product on the other member must be aware of this and perform appropriate verification.

In this environment, if the security product installed on the one member is RACF 1.9, the following considerations apply:

- Jobs submitted on the member without RACF will be verified either when they are converted, or when they go into execution. In order for them to pass this reverification, USER= and PASSWORD= must be specified on the JOB card.
- Jobs submitted on the member without RACF and which are converted and run on that member, cannot be accessed on the member with RACF 1.9 active if the JESSPOOL class is active. All such accesses will fail.
- If any installation exits change the userid associated with a JOB to something other than what was explicitly specified on a JOB card, the JES2 data set names might have inconsistent userids in them.
- Installation might experience problems activating any of the following classes:
  1. JESINPUT
  2. JESJOBS
  3. JESSPOOL
  4. SURROGAT
  5. WRITER

---

## Part 8. Appendixes



---

## Appendix A. IBM Devices Supported by JES2 and How to Use Them

The following provides a list of the devices supported by JES2. JES2 supports all model numbers of devices listed, unless otherwise specified. See *z/OS MVS Migration* for more information about these devices.

- Local Card Readers
  - 2501
  - 2540
  - 3505
  - 3525
- Local Card Punches
  - 2540
  - 3525
- Local Printers (JES2-driven)
  - 1403-N1
  - 3203
  - 3211
  - 3800
  - 4245
  - 4248
- DASD (for Checkpoint and Spool)
  - 3330
  - 3340
  - 3350
  - 3375
  - 3380
  - 3390 (except mod. 9)
  - 9340/45
- Spool Offload Devices
  - Any device supported by DFP
- Remote Workstations
  - BSC Non-Programmable Remotes
    - 2770
    - 2780
    - 3780 and 3781
    - 3770 models which emulate 2780/3780
  - BSC Multi-Leaving Remotes
    - 3777-2
    - S/360 Model 20 (Submodels 2, 4, 5, 6)
    - S/360 Models 22 and subsequent models
    - S/370 Models 115 and subsequent models
    - Workstation Programs on S/36, S/38, AS/400, etc.
  - Remote SNA Workstations (LUTYPE1)
    - 3771
    - 3776
    - 3777-3
    - 3790
    - 8100

Locally attached Print Services Facility (PSF) printers are specified as AFP-1. See *AFP: Printer Information*, G544-3290, for a list of supported device types.

The following devices are not supported by JES2:

- 1403-3 Printer
- 1442 Card Reader
- 1443 Printer
- 2520 Card Reader
- 3540 Diskette Reader/Writer
- S/3 and 1130 as Remote Workstations

---

## DASD Utilization Tables

Table 78 on page 380 shows two things:

1. The storage capacity of various types of devices presented as MBTYPES/VOLUME, BTYES/TRACK, and TRACKS/VOLUME.
2. How JES2 assigns SPOOL devices based on each device's characteristics and where the SPOOLDEF initialization statement parameters have been set with TGFSIZE=30 and BUFSIZE=3992. The values in the table represent what JES2 uses in calculating the available SPOOL Device storage.

For example:

- a. JES2 uses BUFFERS per TRACK of 10 for either 3380s or 9340s and uses a BUFFERS per TRACK GROUP of 30.
- b. JES2 uses BUFFERS per TRACK of 12 for 3390s and sets the BUFFERS per TRACK GROUP to 36.
- c. For a mixture of devices (3380s, 9340s, and 3390s), JES2 starts with TGSIZE=30 and makes the appropriate adjustments for each device types (that is, 3380s and 9340s get 30 BUFFERS/TRACK GROUP and 3390s get 36 BUFFERS/TRACK GROUP).

Once you've identified the device types for use as SPOOL devices and have set your SPOOLDEF initialization statements, you use this table to identify how JES2 utilizes these devices and how JES2 allows for their storage limitations.

Table 78. Calculated Values for Several DASDs

| SPOOL Device Type                                                                                                  |       |       |       |        |        |        |        |        |
|--------------------------------------------------------------------------------------------------------------------|-------|-------|-------|--------|--------|--------|--------|--------|
|                                                                                                                    | 3380  | 3380E | 3380K | 3390-1 | 3390-2 | 3390-3 | 9340-1 | 9340-2 |
| Device Characteristics                                                                                             |       |       |       |        |        |        |        |        |
| MBYTES/VOLUME                                                                                                      | 630   | 1260  | 1890  | 946    | 1892   | 2838   | 1003   | 1502   |
| BYTES/TRACK                                                                                                        | 47476 | 47476 | 47476 | 56664  | 56664  | 56664  | 46456  | 46456  |
| TRACKS/VOLUME                                                                                                      | 13275 | 26550 | 39825 | 16695  | 33390  | 50085  | 21600  | 32340  |
| Values based on BUFSIZE=3992 and TGSIZE=30                                                                         |       |       |       |        |        |        |        |        |
| BUFFERS/TRACK                                                                                                      | 10    | 10    | 10    | 12     | 12     | 12     | 10     | 10     |
| TRKCELL                                                                                                            | 4,5   | 4,5   | 4,5   | 3,4,6  | 3,4,6  | 3,4,6  | 4,5    | 4,5    |
| TRACKS /TRACK GROUP                                                                                                | 3     | 3     | 3     | 3      | 3      | 3      | 3      | 3      |
| BUFFERS /TRACK GROUP                                                                                               | 30    | 30    | 30    | 36     | 36     | 36     | 30     | 30     |
| KBYTES /TRACK GROUP                                                                                                | 120   | 120   | 120   | 144    | 144    | 144    | 120    | 120    |
| TRACK GROUPS /VOLUME                                                                                               | 4425  | 8850  | 13275 | 5565   | 11130  | 16695  | 7200   | 10780  |
| Usable MBYTES/VOLUME                                                                                               | 530   | 1060  | 1590  | 800    | 1600   | 2400   | 862    | 1291   |
| Device Utilization(%)                                                                                              | 84    | 84    | 84    | 85     | 85     | 85     | 85.9   | 85.9   |
| <b>Note:</b> Characteristics of 3390 Model 2. For 3390 Model 1 capacities, divide the volume characteristics by 2. |       |       |       |        |        |        |        |        |

Table 79 on page 381 provides device utilization percentages for selected DASD based on several JES2 initialization parameter BUFSIZE specifications.

Note that the 3390-9 is supported for SPOOL; however you **must** use absolute allocation and the track number cannot exceed 65535 when specified on the SPACE= parameter. For example, specify SPACE=(ABSTR,(64785,30)) on your DD statement for spool or checkpoint allocation. Refer to "Specifying the Storage of Checkpoints on DASD" on page 204 for information on using the SPACE= parameter.

Table 79. Selected Device and BUFSIZE Parameter (on SPOOLDEF) Values and Resultant Utilization Percentages

|                                                                                                            |               |         |                |          | UTILIZATION (%) |
|------------------------------------------------------------------------------------------------------------|---------------|---------|----------------|----------|-----------------|
| DASD                                                                                                       | BYTES /TRACK* | BUFSIZE | BUFFERS /TRACK | DEVICE** | STORAGE***      |
| 3380                                                                                                       | 47476         | 3992    | 10             | 84       | 97              |
|                                                                                                            |               | 3856    | 11             | 89       | 94              |
|                                                                                                            |               | 1944    | 19             | 78       | 95              |
| 3390                                                                                                       | 56664         | 3992    | 12             | 85       | 97              |
|                                                                                                            |               | 3856    | 12             | 82       | 94              |
|                                                                                                            |               | 3768    | 13             | 86       | 92              |
|                                                                                                            |               | 1944    | 22             | 76       | 95              |
| 9340                                                                                                       | 46456         | 3992    | 10             | 85.9     | 97              |
|                                                                                                            |               | 3672    | 11             | 89.6     | 65              |
|                                                                                                            |               | 1944    | 18             | 75.3     | 95              |
| * Values presented as "Maximum Block Size Per Track" in <i>MVS/DFP Managing non-VSAM Data Sets</i>         |               |         |                |          |                 |
| ** Device Utilization % = $\frac{\text{BUFSIZE} \times \text{buffers/track}}{\text{bytes/track}}$          |               |         |                |          |                 |
| *** Storage Utilization % = $\frac{\text{BUFSIZE} \times \text{buffers/page}}{\text{bytes/page}}$ (= 4096) |               |         |                |          |                 |





---

## Appendix B. Miscellaneous JES2 Facilities

This appendix describes some optional JES2 facilities that can help an installation to operate and tune their JES2 member. Some of the facilities described here support other components of the operating system.

The JES2 facilities described are:

- “Automatic Command Processing”.
- “Using the MVS Message Service (MMS) for JES2 Messages” on page 385.
- “Managing Storage in JES2” on page 385.
- “JES2 Spool Data Set Browse” on page 387.

---

### Automatic Command Processing

The operator can specify, from the console or through a local reader, that certain commands or strings of commands take effect automatically at specific times or at regular intervals. The procedures for using the following commands are described in *z/OS JES2 Commands*.

Note that automatic commands can be placed in the initialization deck.

- Start Automatic (\$S A): Starts automatic command processing.
- Set Automatic (\$T A): Displays, specifies, or modifies the strings of commands (the “automatic command elements”).
- Cancel Automatic (\$C A): Cancels all previously entered automatic commands. This command can also selectively cancel selected commands.
- Halt Automatic (\$Z A): Stops all automatic command processing until it is restarted.

Automatic command processing can be used to provide status displays and to lessen the operator’s work for common, preset routines or schedules. For example, if an installation normally does one specific kind of processing at 8 a.m., and another at 9 a.m. every day, it is possible to preset automatic command processing to issue the operator commands that would ordinarily be necessary at those times.

### Writing a Day’s Work Scheduler

Establish the use of automatic command processing with the AUTOCMD parameter on the CONDEF statement at initialization. You can enter the commands with the JES2 \$T command or write a program to put command statements through an internal reader.

Use the T= keyword on the \$T A command to specify the time of day JES2 will issue automatic command(s). T= specifies a time in hours (hh) and minutes (mm) from the previous midnight. Therefore, if the specified time is earlier than the current time, the command is executed immediately. If the time is greater than the current time, the command will be executed hh hours and mm minutes after the last midnight. If the specified time is greater than 24 hours, (note the maximum value for T= is 99.59) a command can be executed up to as many as 3 days, 3 hours, and 59 minutes after the previous midnight. (The time is reset by JES2 each day (at midnight) by decreasing the value by 24 hours.) The following example shows these three situations.

If the current time is 14:00 on Tuesday, then:

```
$TA,T=11.30,'$$ LINE(1)' /*LINE1 started immediately */
$TA,T=15.00,'$$ LINE(2)' /*LINE2 started in one hour */
$TA,T=27.00,'$$ LINE(3)' /*LINE3 started at 03:00 Wed */
$TA,T=51.00,'$$ LINE(4)' /*LINE4 started at 03:00 Thurs */
$SA,ALL
```

Be aware that if these automatic commands are not added to your initialization data set, and JES2 experiences a failure, the commands are lost. You can prevent such situations by adding the commands to your initialization data set or by submitting a `$TA,T=24.01,'$VS,'S D,JOB=jobname'` (where D is a reader procedure and jobname defines a job that contains the series of automatic commands your installation wishes to execute daily) command to automatically recall the job each day. Note that the following example procedure provides a set of automatic commands that are continually refreshed daily.

```
$TA001,T=00.01,'$TRDI,A=0' /*SET INTERNAL READERS' AUTH*/
$TA004,T=00.03,'$VS,'V 02C-02F,ONLINE'' /*VARY PRINTERS ONLINE */
$TA115,T=00.05,'$OJOBQ,Q=B,CANCEL' /*CANCEL CLASS B HELD OUTPUT*/
$TA116,T=07.58,'$VS,'S MANAGMT,JOB=BKUPCTLG'' /* SUBMIT JOB THRU*/
$TA300,T=15.58,'$VS,'S MANAGMT,JOB=BKUPCTLG'' /* MANAGMT PROC */
$TA400,T=23.58,'$VS,'S MANAGMT,JOB=BKUPCTLG'' /* EVERY 8 HRS */
$TA995,T=24.01,'$VS,'S D,JOB=AUTOCMD1'' /*SUBMIT MEMBER TO INTRDR*/
```

The following statements represent sample command statements placed in the initialization data set:

```
$TA,T=10.30,'$$LINE(1-3)'
$TA,T=12.30,'$TI1,C=ABC;TINIT2,C=XBC',L=A
$TA,T=16.15,'$PLINE(1),LINE(3);DMR1-9,'PLEASE SIGN OFF ASAP'
$TA,I=90,'$DPRT2,L=CN3D8-A'
```

These four statements mean the following (and include times of the day set aside for the processing):

1. Start the three remote job entry lines defined.
2. Modify these initiators.
3. Prepare to stop the remote job entry lines and give a warning to users who are currently using the system.
4. Display the attributes of printer 2 every 90 minutes (through the Interval parameter) to out-of-line area A at console CN3D8.

These commands may be set up by a user-written program for scheduling the day's work. This program can use the internal reader to enter the commands in the subsystem. When writing such a program, consider the following:

- When more than one command is to execute at approximately the same time, you should combine them into one command text entry.
- The responses to the command within the text are normally directed to the in-line messages area and to any consoles receiving MCS route code 1, unless you use the L= operand as described in *z/OS JES2 Commands*.
- Multiple commands with responses to the out-of-line area on graphic consoles normally are automatically overlaid so rapidly that the operator cannot view them. Avoid this kind of command sequencing.
- The authority of the internal reader determines which of the commands entered through it will be valid. See *z/OS JES2 Commands* for a discussion of command authority relative to automatic command processing.

- The day's work scheduler program should limit the number of automatic command entries to a value that does not overload the system consoles or leave the operators insufficient resources for their interval status displays.
- An entire automatic command processing entry must fit on an 80-column statement image.

## Limiting Considerations

When automatic command processing is active, commands entered at system speed (rather than at operator speed) may congest the system. In turn, system response to the commands may tend to flood the console with the response messages.

If your installation is experiencing difficulty either with commands congesting the system or messages flooding the console, reevaluate the mix of commands submitted with automatic command processing and try some changes.

Automatic command processing can also end prematurely under the following conditions:

- If the operator enters the \$Z A command to halt automatic command processing and then lets 24 hours or more elapse without restarting it.
- If the operator specifies a start time for automatic command processing that is earlier than the current time, the command will be issued and then cancelled.
- If the operator specifies a start time that does not include an hour specification, but only a minute specification, the command will be cancelled without being issued.
- If the system becomes so congested that the automatic commands are delayed approximately 5 minutes.

Once an automatic command specifying T= has been executed, it must be reentered if it is to be executed at a later time. Make sure the operator fully understands the procedures for using automatic command processing. They are fully outlined in *z/OS JES2 Commands*.

---

## Using the MVS Message Service (MMS) for JES2 Messages

The MVS message service (MMS) provides for the display of JES2 messages in languages other than English, including languages that require a double-byte character set. For more information about MMS, see *z/OS MVS Programming: Assembler Services Guide*.

---

## Managing Storage in JES2

Most JES2 code in common storage resides above 16 megabytes in virtual storage, while all JES2 code in private storage resides below 16 megabytes in virtual storage. All JES2 code runs in 31-bit addressing mode, except those sections of JES2 code that deal with calls to restricted MVS services (such as the FSI). JES2 uses 31-bit addressing to reduce its use of the common storage area (CSA) below 16 megabytes in virtual storage.

Some JES2 control blocks reside below 16 megabytes in virtual storage, because these control blocks need to reference other MVS control blocks that also reside there. (For a list of these control blocks, refer to *z/OS JES2 Installation Exits*.)

If you require further information on JES2 when operating in 31-bit addressing mode, to include coding specifics, control block residency, required linkage conventions, or the changes to several assembler instructions (to provide compatibility with the operating system code) refer to *z/OS JES2 Installation Exits* and *z/OS MVS Programming: Assembler Services Guide*.

## Storage Considerations

The careful specification of several initialization parameters enables you to optimize both central and virtual storage. The following sections can help you optimize storage use and aid performance of your system.

### JES2 Private Area Virtual Storage

The checkpoint data set, NJE and RJE line control blocks, RJE device control blocks, and spool buffers can require large amounts of virtual storage. Also, teleprocessing buffers, offload transmitters and receivers, networking lines, JES2 code, and installation modifications consume additional virtual storage. Therefore, to minimize JES2 private area size below 16 megabytes in virtual storage, take care not to overspecify the initialization parameters listed in the following table.

| Initialization Statement | Parameter            |
|--------------------------|----------------------|
| BUFDEF                   | BELOWBUF LIMIT       |
| TPDEF                    | BSCBUF LIMIT<br>SIZE |

### Central Storage

Control use of central storage space by carefully specifying the value for the TRKCELL parameter on the SPOOLDEF initialization statement. The following notes should assist you, if you experience central storage constraints.

- Two copies of the checkpoint data set reside in virtual storage.
- If your installation has a 3800-1 printer operated by JES2 and track-cell despooling and double buffering are in effect, the number of central storage frames is two times the value of TRKCELL during printing activity. (If you set the BUFSIZE= parameter on the SPOOLDEF statement to its lower limit, 1944, you only need TRKCELL= number of frames.)

Also, note that as your installation adds printers to its configuration, JES2 central storage requirements increase proportionally.

JES2 obtains the buffer storage requirements for printers operated by a functional subsystem from the functional subsystem address space private area and page-fixes the storage. Therefore, these buffers do not affect JES2 virtual storage usage, but they increase the use of central storage.

### Storage Isolation

JES2 has specific storage requirements. If you do not set aside sufficient central storage for JES2, your system can suffer any combination of the following symptoms:

- The system runs in an extremely degraded state.
- The number of remote job entry (RJE) time-outs increases.
- System tasks initiate slowly.
- System lock-out messages occur in multi-access spool configurations.

If your system performance exhibits these symptoms, we recommend the use of storage isolation. Also, if your installation requires only certain functions (for

example, RJE) during certain periods of the day, you should specify a fairly wide range of storage isolation values, in order to free up some central storage when those functions are not in use. The technique for specifying storage isolation for JES2 is the same as for any other MVS address space. You can adjust the appropriate level of storage isolation for your JES2 system by using parameters in the installation performance specifications (IPS) member of SYS1.PARMLIB. (Refer to *z/OS MVS Initialization and Tuning Reference* for a complete description of this technique.)

## Job Journaling, SMF Records, and SMF Exits

To reduce overhead, request job journaling explicitly only when needed and turn off unused JES2-generated SMF records and exits (unless you need them for analysis). Measurements have shown a significant (up to 34%) increase in overhead caused by journaling virtual I/O on a system with a workload of many steps.

To bypass journaling and turn off SMF records, specify the following parameters on the JOBCLASS(v) initialization statement: JOURNAL=NO, TYPE6=NO, TYPE26=NO, IEFUJP=NO, IEFUSO=NO, and LOG=NO. The default for each is YES; therefore, you must specify these to turn off journaling. Turning off SMF records has an impact on your ability to audit security-related events. Before suppressing SMF records, you should discuss the implications with your security administrator.

For more information about these parameters and the JOBCLASS(v) statement, refer to the JOBCLASS statement description in *z/OS JES2 Initialization and Tuning Reference*.

## Spool Utilization

Correct performance problems related to spool capacity or I/O efficiency by properly specifying the following initialization parameters: BUFSIZE=, TGSPACE=(MAX=), TRKCELL=, and TGSIZE= on the SPOOLDEF statement. Refer to the individual description of each in *z/OS JES2 Initialization and Tuning Reference* and the device utilization statistics tables, “DASD Utilization Tables” on page 379.

---

## JES2 Spool Data Set Browse

Spool data set browse (SDSB) is a function application programs can invoke to process spool data sets. JES2 provides an interface that application programs can use for this purpose. SDSB can be used to access data sets that are still open in running address spaces. Any full data buffers that have been written to SPOOL can be read and optionally, data that has not been written (unwritten buffer support) can also be accessed (provided the application is running on the same system where the target data set is open).

Only authorized programs can use SDSB to allocate SPOOL data sets. The data set being requested is specified by passing the JES2 data set name along with a SPOOL browse token to MVS dynamic allocation. Once the data set is allocated, the data set can be read using one of two methods:

1. Using the compatibility interface (DCB, GET).
2. Using the ACB/RPL interface.

You use the compatibility interface when synchronous sequential access is required. You use the ACB/RPL interface when random access to the spool file is required, or when asynchronous processing is desired.

## Allocation

JES2 recognizes a spool data set browse allocation when a SPOOL browse token is specified on a dynamic allocation call. The SPOOL browse token is specified along with the data set name and contains optional control information JES2 uses to allocate the desired data set. SDSB can only be specified on dynamic allocation requests, and the following text units are required on the dynamic allocation request:

- DALDSNAM (data set name, set from PDBDSNAM)
- DALSTATS (disposition = SHR)
- DALSSREQ (subsystem name)
- DALBRTKN (browse token)

Other text units are optional (for example, DALRTDDN, used to return the ddname allocated to the data set).

**Note:** The DALSSREQ text unit can only be specified by authorized programs, and the allocation must be performed in authorized state. After the allocation is complete, an unauthorized task can perform I/O operations on the spool data set.

The JES2 data set name is passed to dynamic allocation using the DALDSNAM key. The format of the data set name is:

userid.jobname.jobid.Ddskey.dsname

If the exact data set name is not known, the generic characters '?' and '\*' can be used in the data set name. However the jobname and jobid are required. In the event that more than one data set matches the data set name requested, then the first data set that matches is allocated.

An alternate data set name is also supported. This provides access to certain JES2 system data sets (without needing to know the exact data set name). The alternate format is:

userid.jobname.jobid.jes\_dsname

where jes\_dsname is one of the following:

- JCL - This is the input JCL (including the SYSIN data sets) exactly as submitted
- JESJCLIN - Same as JCL
- JESJCL - JCL images as output by the converter
- JESMSGLOG - JES2 message log (WTOs issued by the job)
- JESYSMSG - JES2 system messages

Prior to issuing the dynamic allocation request, the application must build the browse token and pass it with the DALBRTKN text unit. The format of the browse token is mapped by macro **IAZBTOKP**. The browse token is built in text unit format with 7 subparameters. When building the browse token, the following SVC 99 text unit fields must be set:

| Field    | Value              |
|----------|--------------------|
| S99TUKEY | DALBRTKN           |
| S99TUNUM | 7                  |
| S99TUPAR | Mapped by IAZBTOKP |

The token is of fixed length and all subparameters must be coded. Each browse token subparameter contains a length followed by the data, so it will be in text unit format.

You complete the fields in the token as follows:

**BTOKPL1**

is the length of the browse token identifier (LENGTH(BTOKID)).

**BTOKID**

Browse token id (BTOK). The IAZBTOKP macro defines constant BTOKCID to be used to set this field.

**BTOKPL2**

Length of the token version field (LENGTH(BTOKVER)).

**BTOKVER**

The 2 byte version number of the token parameter list. Byte 1 (or TOKTYPE) indicates the call type. If set to BTOKBRWS, then this is a normal browse request. If set to BTOKSTKN then this is a SPOOL token based browse request. Byte 2 (or BTOKVERS) is the parm list version and should be set to BTOKVRNM.

**BTOKPL3**

Length of the IOT MTTR field (LENGTH(BTOKIOTP)).

**BTOKIOTP**

Data pointer, content is based on the first byte of BTOKVER. If set to BTOKBRWS, then this is the optional MTTR of the IOT containing the PDDb of the file to be allocated (obtained from JOEIOTTR or IOTTRACK, for example). If BTOKVER is set to BTOKSTKN, this must be either a client token (returned from dynamic allocation using key DALRTCTK) or a data set token (returned by SAPI in field SSS2DSTR.)

**BTOKPL4**

Length of the job key field (LENGTH(BTOKJKEY)).

**BTOKJKEY**

Optional job key of the file to be allocated (obtained from JCTJBKEY, JQEJBKEY, or SJBKEY, for example). This field is not used if BTOKVER is set to BTOKSTKN. This field is required if BTOKTYPE is set to BTOKBRWS and BTOKIOTP is non-zero.

**BTOKPL5**

Length of the asid field (LENGTH(BTOKASID)).

**BTOKASID**

The 2 byte ASID of the data set owning job if the job is active on the same system and active buffers are needed. If active buffers are not needed, then pass 0. If the ASID is not known, then pass X'FFFF' and JES will determine the correct ASID.

**BTOKPL6**

Length of the RECV field (LENGTH(BTOKRCID)).

**BTOKRCID**

Eight byte userid to be used as the RECV on the SAF call used by JES2 to check authority to the browse request, or zeros if the RECV is not being used. When RECV is used, the value must be left justified and padded with blanks.

When this parameter is specified, the *logstr* field should also be used so that usage of *recvr* can be logged. However, neither JES2 nor SAF enforce this convention.

**BTOKPL7**

Length of the *logstr* field (LENGTH(BTOKLOGS)).



### **BTOKLSDL**

Length of the *logstr* (specified in field BTOKLSDA) to be used on the SAF call used by JES2 to check authority to the browse request, or zero if the *logstr* is not being used.

The *logstr* length must be a value from 0 to 254.

### **BTOKLSDA**

Text of the *logstr* if BTOKLSDL is non-zero, or zeros if the *logstr* is not being used.

The maximum length text is 254 characters.

**Note:** When you use the compatibility interface to read the data set, you also use text units specifying the record format, record length, and blocksize.

### **Security**

No SAF call are performed by JES2 during allocation. When the SPOOL data is opened, JES2 uses SAF to verify read access to the JESSPOOL resource associated with the data set. The resource name is then constructed using the data set name passed on the allocation request. Any generic characters are replaced by the actual values for the data set allocated.

If the browse token specifies a *recvr* userid, the SAF call is performed with the RECVR parameter. When the *recvr* userid is specified, the *logstr* parameter should also be supplied.

If the data set fails the security check, the open request fails with R15=0C and an error code stored in ACBERFLG (decimal 152).

### **Errors and Return Codes**

If an error occurs allocating the data set, dynamic allocation returns a reason and return code describing the error. You can use the system's **daifail** service to format the error text. If an error occurs during data set open, a return code is set in register 15 following the OPEN and a reason code stored in the ACB.

## **Using the Compatibility Interface**

After you allocate the spool data set, use the compatibility interface to sequentially read each record. Your application program builds and opens a DCB that specifies the ddname of the allocated spool data set. If the record format, record length, and block size are not specified on the allocation, they must be specified in the DCB. If there is no record format, LRECL or block size on the allocation or DCB, it will be obtained from the SYSOUT data set that was allocated.

The system performs a SAF call as part of OPEN processing to ensure that the user is authorized to the data set. If the user is not authorized, a system abend, code S913, results. After the DCB has been opened, use a GET macro pointing to the DCB to read the file. When processing is complete, use a CLOSE macro to close the file. The same task that opened the DCB must be used to close it.

## **Using the ACB/RPL Interface**

Your application can use the ACB/RPL interface to obtain the most flexibility when using spool data set browse (SDSB). With this method, the application builds and opens an ACB (access method control block), and uses RPL based macros to read and position the data set. You use a subset of the ACB/RPL macros as documented for VSAM. In general, JES implements only those features required to process the

data set. Other options specified on the macros are ignored. When coding the ACB and RPL macros, AM=VSAM should be specified or defaulted.

### Building the ACB

After the dynamic allocation completes for the data set, your application builds and opens an ACB. You can use the GENCB serve or map the ACB with IFGACB macro. The storage for the ACB must be resident below the 16 megabyte line. You then use the SHOWCB and MODCB services to display and modify selected fields of the ACB. However, some of the fields required by JES are not processed by those services, and hence they may be of limited use. The only required field for the ACB is the ddname to use. The ddname can be assigned when the spool data set is allocated, or the system can return a generated name. In either case, the ACBDDNAM must be completed before the ACB is opened.

**Note:** The ACB can also specify an optional exit list. The exit list is built with the EXLST macro, and can be used to specify the EODAD, SYNAD, and LERAD exits.

Once the ACB is generated, your application opens it using an OPEN macro. As part of open, the system performs a SAF call to ensure that the user is authorized to the data set. If the user is not authorized, a S913 ABEND results.

**Note:** Unless authorization has changed between the time the data set was allocated and opened, an unauthorized user will be detected at allocation time.

After the open is successful, you use RPL based macros to read the data set. If the open is not successful, error and reason codes that describe the error are placed in the ACB.

When processing is complete, your application should issue a CLOSE macro specifying the open ACB. If a CLOSE is not performed, an automatic close occurs by the system when end-of-task occurs. The close must be done by the same task that opened the ACB.

**Requesting Carriage Control:** The spool data set browse (SDSB) interface can be used to obtain the carriage control character if it is contained in the record. The spool data set browse interface returns carriage control with the record only if it is requested. Your application indicates that carriage control is wanted by setting flag ACBCCTYP as follows:

- ACBCCTYP.ACBCCASA = ON indicates that ASA characters are wanted.
- ACBCCTYP.ACBCCMCH = ON indicates that machine characters are wanted.

Both bits can be turned on to indicate that carriage control is desired regardless of format. When a data set contains carriage control, and the application requests carriage control for that type, the control character will be returned in the first byte of the record area returned by JES2.

If the data set does not contain carriage control, but the application requests carriage through the setting of ACBCCTYP, JES2 performs the following:

- If ACBCCASA is on, JES2 returns a X'40' as the carriage control.
- If ACBCCMCH is on, JES2 returns a X'09' as the carriage control.
- If both ACBCCASA and ACBCCMCH are on, JES2 returns a X'09' as the carriage control.

## Using the Compatibility Interface

### Using RPL Based Macros

All I/O requests are specified using an RPL. The RPL contains the address of an open ACB. You build the RPL using the GENCB service, or map it with the IFGRPL macro. You can then use SHOWCB and MODCB for some functions. The storage for the RPL must be resident below the 16 megabyte line.

The processing options are specified in the RPLOPTCD parameter. Only a subset of those defined by VSAM are recognized by JES2. In particular, spool data set browse supports only "move mode" (OPTCD=MVE) processing. OPTCD=SYN can be specified for synchronous requests (the default), or OPTCD=ASY can be used for asynchronous processing.

Your application must obtain a buffer area where JES2 places the record it reads. The address of the area is placed in RPLAREA and its length in RPLBUFL. If the area is not large enough to contain the record, JES2 sets an error code in the RPL. The storage for the buffer may be resident above the 16 megabyte line.

Your application reads each record using a GET macro which points to the RPL. When synchronous processing is used, control returns to the application when the GET is complete and the record has been moved to the application provided area. JES2 sets the length of the returned record in field RPLRLN.

When asynchronous processing is used, your application must issue a CHECK macro specifying the RPL that is to be waited on. Control then returns to your application when the function specified by the RPL is complete.

After each GET request, JES2 returns a token your application can use to position directly to the record if it needs to be reread. JES2 returns the 8 byte token in field RPLRBAR after each GET. Your application should treat RPLRBAR strictly as a token, and not depend on it to be in a specific format.

Your application can use the POINT macro to locate a previously read record. POINT specifies an RPL that contains an RPLRBAR that was returned on the GET request for the desired record. POINT positions JES2 to the record to be read; it does not read the record. A GET macro must be issued after the POINT to retrieve the record.

Each GET request returns a logical record in the file. The application is isolated from the internal format of the record. JES2 places the complete record in the RPLAREA buffer and its length in the RPLRLN field. JES2 performs the necessary unwritten buffer support for active jobs; however, no indication of the source of the record is placed in the RPL. JES2 places feedback information in the RPL after each request. RPLRTNCD and RPLCNDCD should be checked for satisfactory completion after each operation.

## End of File Processing

For jobs not running, the spool data set browse (SDSB) interface utilizes the end-of-file exit when no more data can be read. When using the compatibility interface, the exit is defined using the EODAD parameter of the DCB. When using the ACB/RPL interface, the end-of-file exit is defined on the EXLST macro. In addition, the return codes are placed in the RPL to indicate the end of file condition.

For jobs actively running, using the ACB/RPL interface, your application attempts to read unwritten spool buffers that reside in the address space of the active job. When all unwritten buffers have been read, the ACB/RPL utilizes the end-of-file exit.

## Using the Compatibility Interface

Your application can issue subsequent get requests to obtain additional data. On each get request, the ACB/RPL interface returns the unwritten buffer data, if available. Thus, an end of file condition for an active job should be considered temporary rather than permanent. As the active job creates additional data, subsequent get requests can be used to retrieve it. If no more data is available at the time of the get, end of file will be driven.

**Note:** This processing differs from standard access methods. Normally, a get request issued after end of file is considered as a permanent error. However, this condition should be expected when using the spool data set browse interface against an active job.

## Performance

Spool data set browse (SDSB) presents a record level interface (that is, a complete record is returned on each get request). If a record is internally stored in several JES2 spool blocks, your application's use of the interface performs the necessary spool I/O to assemble the record segments. JES2 maintains only one spool buffer in storage at a time. Similarly, if a POINT macro is issued for a record not contained in the last spool block, JES2 initiates the I/O to read the block.

Your application can improve the performance of the interface by optimizing the number of I/O requests. For example, you might want your application to buffer previously read records in storage, rather than call the interface with POINT and GET to reread a record.

## Secondary Subsystem Support

The spool data set browse (SDSB) interface supports allocation of spool data sets to secondary JES2 subsystems. You specify the subsystem name in the DALSSREQ text unit and direct the allocation to the proper JES2.

**Note:** A secondary subsystem cannot be halted until all outstanding allocations are freed.

## Using the Compatibility Interface

---

## Appendix C. The External Writer

This appendix documents Product-sensitive Programming Interface and Associated Guidance Information.

An external writer allows an installation to perform output processing for data sets not eligible for processing by the primary job entry subsystem (JES2 or JES3). For example, an external writer processes data sets going to printers, plotters, diskettes or data sets that are to be stored on a device not supported by JES.

There are two major parts of the IBM-supplied external writer that can be modified or replaced by an installation: the output writing routine and the output separator routine.

This chapter describes:

- Overview of the IBM-supplied external writer
- How to set up and start the IBM-supplied external writer
- How the IBM-supplied output writing routine works
- How to add your own output writing routine
- How the IBM-supplied output separator routine works
- How to add your own output separator routine

See *z/OS MVS Using the Functional Subsystem Interface* for information in subsystem interface (SSI) function code 1 on how to write your own external writer.

---

### Overview of the IBM-Supplied External Writer

IBM supplies an external writer, which contains two routines that can be modified or replaced by the installation:

- The output writing routine. This routine processes data sets.
- The output separator routine. This routine writes separator records within a continuous listing or deck to help the operator separate one job's output from another's.

### Characteristics of the IBM-Supplied External Writer

The external writer has the following features:

- It runs as a started task, in its own address space, in 24-bit addressing mode
- It processes only those data sets that meet its selection criteria. You set some of these in a cataloged procedure (see "The External Writer Cataloged Procedure" on page 396) but you can override them with the START and/or the MODIFY operator commands (see *z/OS MVS System Commands* for the general description of these commands).

If you do not specify data set selection criteria, the external writer will be used to process **all** the output in the system.

- It removes data sets from the JES spool. That is, it dynamically allocates the data sets, reads them, writes them to output devices, and then dynamically deallocates them.
- It accesses data sets according to one or more of the following criteria:
  - Output class
  - Job ID
  - Forms specification
  - Destination (LOCAL, or remote workstation name)

- The name of your output writing routine

The usual technique however, for setting data set selection criteria, is to build a list of eligible SYSOUT classes for the devices that will use the external writer.

---

## How to Set Up and Start the External Writer

For an external writer to work in a JES environment, it must be defined to the system in a cataloged procedure residing in SYS1.PROCLIB; and it must be started by a START command, either from the system console or from within a program.

There are two ways to set up the criteria by which the external writer selects output. The PARM= field (described below) allows the specification of SYSOUT classes to select. Other criteria (such as forms, destination, writer name, jobid and also SYSOUT class) must be specified using the MVS MODIFY command. See *z/OS MVS System Commands* for a complete description of the modify command as it applies to the external writer.

## The External Writer Cataloged Procedure

The IBM-supplied external writer is defined and invoked by the cataloged procedure named XWTR, which can serve as the base or a model for a procedure you would write for your own output writer.

XWTR contains one step and consists of two JCL statements:

- The EXEC statement specifies the name of the external writer program to be executed.
- The DD statement, which **must** be named IEFRDER as shown below, defines the output data set.

Following is the actual XWTR procedure:

```
//IEFPROC EXEC PGM=IASXWR00,REGION=20K, X
// PARM='PA,, '
//IEFRDER DD UNIT=TAPE,VOLUME=(,,35), X
// DSN=SYSOUT,DISP=(NEW,KEEP), X
// DCB=(BLKSIZE=133,LRECL=133,BUFL=133, X
// BUFNO=2,RECFM=FM)
```

### The EXEC Statement

The generalized format for the EXEC statement is:

```
//IEFPROC EXEC PGM=IASXWR00[,REGION=nnnnnK,]
// [PARM='cxxxxxxx[,seprname]] '
// [PARM='cxxxxxxx[,seprname][,CERTIFY=Y|N]] '
```

The stepname must be IEFPROC, as shown. The parameter requirements are as follows:

#### PGM=IASXWR00

The name of the external writer load module. It must be IASXWR00, as shown.

#### REGION=nnnnnK

This parameter specifies the region size for the external writer program. The value nnnnn is a 1- to 5-digit number that is multiplied by 1K (1024 bytes) to designate the region size. The region size can vary according to the size of buffers and the size of your output writing routine. Insufficient region size will cause the external writer to abend.

**[PARM='cxxxxxxx[,seprname][,CERTIFY=Y|N]]'**



**[PARM='xxxxxxxx[,seprname]]'**

Specifies output writer routine characteristics.

- c** An alphabetic character, either **P** (for printer) or **C** (for card punch), that specifies the control characters for the class of output the output writing routine will process.

**xxxxxxxx**

From one to eight (no padding required) single-character SYSOUT class names. These characters specify the classes the output writing routine will process and establish the priority for those classes, with the highest priority at the high-order (leftmost) end of the character string.

**Note:** If the START command includes class name parameters, they override all of the class names coded here. If you do not code class names on the procedure EXEC statement or the START command, then the external writer will wait for a MODIFY command from the operator before processing any output.

**seprname**

This is the name of the output separator routine to run with the output writing routine. If you omit this subparameter, no output separator pages are produced.

IEFSD094 is the IBM-supplied output separator routine. If you write your own output separator routine, and name it here, put it in SYS1.LINKLIB (or a library concatenated to LINKLIB through a LNKSTxx member of parmlib).

**Note:** Do not use *CERTIFY* as the name of your output separator routine. For your separator routine to be invoked, you must either code its name on this subparameter or name it in the parameters on the START command.

**CERTIFY=YIN**

Indicates whether (Y) or not (N) you want to ensure that all data is safely written to the output device. CERTIFY=Y indicates that data will **not** be lost even if the external writer abnormally terminates, such as would occur if the output data set becomes full.

**Notes:**

1. The use of the certify function increases processing overhead and decreases efficient space utilization by the output data set.
2. If you write your own output writing routine and require the CERTIFY function, you need to modify your code to be similar to that supplied by IBM. Refer to "Using the CERTIFY Function" within section "Programming Considerations for the Output Writing Routine" on page 404 for further details.
3. IBM cannot guarantee data set integrity when writing multiple data sets to a PDS/PDSE member even if you specify CERTIFY=Y. Refer to "Functions of the Output Writer Routine" on page 400 for further details.

**The DD Statement**

In this statement, you must define the output data set that the external writer will use. The generalized format for the DD statement is:

```
//IEFRDER DD UNIT=device,LABEL=(,type), X
// VOLUME=(,,volcount),DSNAME=anyname, X
// DISP=(NEW,KEEP),DCB=(list of attributes), X
// UCS=(code[,FOLD][,VERIFY]), X
// FCB=(image-id[,ALIGN][[,VERIFY])
```

The ddname must be IEFRDER, as shown. The parameter requirements are as follows:

**UNIT=device**

This specifies the printer, tape, card punch, or DASD device on which the output data set is to be written.

**LABEL=type**

This describes a data set label, if one is needed (for tape data sets only). If this parameter is omitted, a standard tape label is used.

**VOLUME=(,,volcount)**

Needed for tape data sets only, this parameter limits the number of tape volumes that this external writer can use during its entire operation.

**DSNAME=anyname**

This specifies a name for the output data set, so later steps in the procedure can refer to it. The data set name is required for the disposition of KEEP.

**DISP=(NEW,KEEP)**

The disposition of KEEP prevents deletion of the data set (tape and DASD only) at the end of the job step.

**DCB=(list of attributes)**

The DCB parameter specifies the characteristics of the output data set and the buffers. The BLKSIZE and LRECL subparameters are always required. The BUFL value, if you do not code it, is calculated from the BLKSIZE value. Other subparameter fields may be coded as needed; if they are not, the defaults are the QSAM default attributes. These are:

**BUFNO—**

Three buffers for the 2540 punch; two buffers for all other devices.

**RECFM—**

U-format, with no control characters.

**TRTCH—**

Odd parity, no data conversion, and no translation.

**DEN—**

Lowest density.

**OPTCD—**

Printer data checks are suppressed, and “select translate table” characters are printed as data. The IBM external writer does not support OPTCD=J, a 3800 printing subsystem specification.

**UCS=(code[,FOLD][,VERIFY])**

This specifies the code for a universal character set (UCS) image to be loaded into the UCS buffer.

FOLD causes bits 0 and 1 to be ignored when comparing characters between the UCS and print line buffers, thereby allowing lowercase alphabetic characters to be printed (in uppercase) by an uppercase print chain or train.

VERIFY causes the specified UCS image to be printed for verification by the operator.

The UCS parameter is optional, and is valid only when the output device is a 1403, a 3211, or a 3203-5 printer.

**FCB=(image-id[,ALIGN][,VERIFY])**

This causes the specified forms control buffer (FCB) image to be loaded into the FCB. ALIGN and VERIFY are optional subparameters that allow the operator to align forms. In addition, VERIFY causes the specified FCB image to be printed for visual verification. The FCB parameter is valid only for a 3203-5, 3211, or 3800 printer; otherwise, it is ignored.

See *z/OS MVS JCL Reference* for more information on the parameters mentioned here.

**Special Printer Output Considerations:** To process output jobs that require special chains for printing, you should have specific classes for each different print chain. You can specify the desired chain in your output writer procedure, and when that output writer is started, the chain will be loaded automatically. (Printers used with special chains should be named with esoteric group names as defined at system installation.) See *z/OS HCD Planning* for information on the eligible device table.

Following is an example of the JCL needed to define a special print chain in a cataloged procedure for an external writer.

```
//IEFPROC EXEC PGM=IASXWR00,REGION=20K,PARM='PDEG,IEFSD094'
//IEFRDER DD UNIT=SYSPR,DSNAME=SYSOUT,FCB=(STD2,ALIGN), X
// UCS=P11,DISP=(,KEEP), X
// DCB=(BLKSIZE=133,LRECL=133,BUFL=133, X
// BUFNO=2,RECFM=FM)
```

In this example, the UCS DD parameter requests the print chain alias for data sets in the SYSOUT classes D, E, and G.

If the output device is a 3211 or a 3203-5, a UCS or FCB image can be loaded dynamically between the printing of data sets. Therefore, you can specify a mixture of data sets using different images in a single output class for this device. This will probably require mounting trains and changing forms, however, so it might not be desirable.

When the output device is a 1403 or 3800, the UCS image or 3800 attributes are specified at START XWTR time; they cannot be changed until the writer is stopped. Therefore, all data sets within an output class must be printed using the same train.

The FCB image is ignored when the 1403 printer is the output device.

External writer output to an IBM 3800 Printing Subsystem can also make use of the CHARS, COPIES, FLASH, and MODIFY JCL parameters on the DD statement. For information about using these parameters, see *3800 Printing Subsystem Programmer's Guide*. The coding rules and defaults are documented in *z/OS MVS JCL Reference*.

---

## How the IBM-Supplied Output Writer Routine Works

As stated previously, there are two main pieces to the external writer that can be modified or replaced by the installation: The output writer routine and the output separator routine. When the external writer is called, it gets control in module IASXWR00. The main function of IASXWR00 is to initialize a 7-word parameter list for the use of the other external writer routines.

The parameter list contains information about the output device and DCB addresses for each data set. The input data set to the external writer was a job's output data set which met the criteria for processing by the external writer. This input data set is not yet open.

The format of the external writer parameter list is as follows:

*Table 80. External Writer Parameter List*

| Byte  | Meaning                                                                                                                                                                                                                                                                                                                                                                          |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 0     | Used to describe the type of output device <div> <div> <b>Bit</b> <b>Meaning</b> </div> <div> <b>011. ....</b> 2540 punch unit </div> <div> <b>001. ....</b> <br/>1403, 3203-5, 3211, or 3800 printer device </div> <div> <b>010. ....</b> <br/>tape device with punch-destined output </div> <div> <b>000. ....</b> <br/>tape device with printer-destined output </div> </div> |
| 1-3   | Reserved for IBM use                                                                                                                                                                                                                                                                                                                                                             |
| 4-7   | Address of the DCB for the opened output data set where the external writer will put the input records                                                                                                                                                                                                                                                                           |
| 8-11  | Address of the DCB for the input data set, from which the external writer will obtain logical records.                                                                                                                                                                                                                                                                           |
| 12-15 | Address of the cancel ECB for writer routine subtask (IEFSD087 or user-written writer routine).                                                                                                                                                                                                                                                                                  |

The switches indicated by the three high-order bit settings in byte 0 can be used in translating control character information from the input records to the form required by the output device.

## Functions of the Output Writer Routine

When you specify IEFSD087 as the output writer on the SYSOUT= parameter of the DD statement, or when you leave this parameter blank, control will pass to the IBM-supplied output writing routine in module IEFSD087, and it:

- Issues an OPEN (J type) for the input data set previously taken from the JES spool.
- Provides its own SYNAD error-handling routine on behalf of both the input and output data sets. See *z/OS DFSMSdfp Advanced Services* for more information about OPEN-J and SYNAD.
- Reads the input data set, using the locate mode of the GET macro.
- Calls a subroutine to handle ANSI and machine control character differences and to handle conversions between the input records and the output data set
- Calls a routine to write records to the output data set, using the locate mode of the PUT macro
- Closes the input data set after it has been read
- Provides accounting support by updating fields in the SMF type 6 record for the input data set
- Frees the buffer associated with the input data set (by issuing the FREEPOOL macro)
- Returns control to the main logic control module of the external writer, IASXWR00, using the RETURN macro and setting a return code.

**Note:** When writing multiple data sets to a PDS/PDSE member, if the 'end-of-output-data-set' condition arises, the output external writer cannot guarantee (even if you set CERTIFY=Y as a startup parameter) that all records will be saved. The current data set is saved, but all records written up to that point cannot be recovered in the case of writing to a PDS/PDSE member.

The following diagram shows the general flow of the IBM-supplied output writing routine:




Figure 80. General Flow of IBM's Output Writing Routine

---

## How to Add Your Own Output Writing Routine

If you want to add your own output writing routine to the external writer, consider whether your routine will be needed more often than the IBM-supplied routine. If your routine will be invoked to write **most** of the external writer's output, you might want to replace the IBM-supplied with your own routine, so that your routine will be called by default. You can retain the IBM-supplied routine by renaming it to an alias.

### Replacing the IBM-Supplied Routine

You can replace the IBM-supplied routine with your routine by:

- Renaming the IBM-supplied routine (IEFSD087) to an alias.
- Naming your routine IEFSD087
- Installing your routine in SYS1.LINKLIB

The external writer will call your routine by default. You can request the IBM-supplied routine by coding its alias on the SYSOUT= parameter. For example:

```
//MYDATA DD SYSOUT=(H,IBMWRITR)
```

where IBMWRITR is the alias you've given to the IBM-supplied routine.

Do not code STDWTR as a writer name. STDWTR and INTRDR are and are reserved for JES used as a parameters in the MVS operator's MODIFY command.

In a JES3 system, do not code NJERDR as a writer name. NJERDR is reserved for JES3.

### Using Your Routine for Only Certain Jobs

If you plan to have your routine invoked for only certain jobs, give it a unique name, and install it in SYS1.LINKLIB or an authorized library concatenated to LINKLIB through a LNKSTxx member of SYS1.PARMLIB. To have your routine invoked, the end-user must specify its name on the SYSOUT= parameter of the job's DD statement. When your routine is not specified, the system calls the IBM-supplied routine by default.

### Coding Conventions for the Output Writing Routine

In order for your output writing routine to work in the external writer, it must observe the following conventions:

- If you put your routine in LPA so that you only use one copy for all external writers, then it must be reentrant. If you use a STEPLIB and each writer can have its own copy, then the code need not be reentrant.
- The routine must use standard entry and exit linkage, saving and restoring its caller's registers.

At entry, register 1 points to the parameter list and register 13 points to an 18-word save area.

- The routine must issue an OPEN-J macro to open the desired input data set. The data set to which the output writing routine will write records is opened before the routine is loaded.
- The routine must use the GETMAIN and FREEMAIN macros, or the STORAGE macro, to acquire and release any necessary storage.
- The routine must return control to its caller through the RETURN macro, in the same addressing mode it was called in. It must put a return code in register 15:
  - A return code of 0 indicates that the data set was processed successfully to the output device.



- A return code of 8 indicates that the routine was unable to process the data set because of an output error.

## Programming Considerations for the Output Writing Routine

In addition to the coding conventions, consider the following when writing your own output writing routine:

- **Obtaining Storage for Work Areas:** Using the GETMAIN or STORAGE macro, the output writing routine should obtain storage in which to set up switches and save record lengths and control characters.
- **Processing an Input Data Set:** To process a data set, the writing routine must get each record individually from the input data set, transform (if necessary) the record format and the control characters to conform to the output data set's requirements, and put the record in the output data set. Consider each of these tasks individually:

1. Before the routine actually obtains a record from an input data set, the routine must provide a way to handle the two forms of record control character that are allowed in an output data set, if the output device is a printer.

Most printers are designed so that, if the output data set records contain machine control characters, a record (line) is printed before the effect of its control character is considered. However, if ANSI control characters are used in the output records, the control character's effect is considered before the printer prints the line. Thus, if the input data sets do not all have the same type of control characters, you will need to avoid overprinting the last line of one data set with the first line of the next.

When the input records have machine control characters and the output records are to have ANSI control characters, the standard (IBM-supplied) output writing routine produces a control character that indicates one line should be skipped before printing the first line of output data.

When the input records have ANSI control characters and the output records are to have machine control characters, the standard writing routine prints a line of blanks before printing the first actual output data set record. Following this line of blanks, the printer generates a one-line space before printing the first record.

Depending upon the characteristics of the printers in your installation, you will probably want your output writer to perform some kind of "printer initialization" like that outlined here.

2. After the output writing routine has properly opened the input data set and has completed any necessary printer initialization, it must obtain records from the input data set.

The standard output writing routine uses the locate mode of the GET macro. If you use this macro, you will need to check the MACRF field of the input data set's DCB to see if GET in locate mode is allowed. If not, you can override the MACRF parameter on the GET macro itself. See *z/OS DFSMSdfp Advanced Services* for information on coding and using all the QSAM macros.

In a JES2 system, the padding is done automatically.

In a JES3 system, if blank truncation is in effect (TRUNC=YES specified on the BUFFER initialization statement or the SYSOUT initialization statement), then fixed format records will not be padded with blanks. You need to do the padding manually.

3. Having obtained a record from the input data set, the output writing routine must now make sure that its format and control character are compatible with the requirements of the output data set.

Because the output data set is already opened when the output writing routine is entered, your routine will have to adhere to the established conventions.

The standard output writing routine uses the PUT macro in the locate mode to write records to the output data set. For fixed-length output, it obtains the record length for the output data set from the DCBLRECL field of the DCB.

If an input record is longer than the length specified for the output records, the standard output writing routine truncates the input record from the right.

If an input record is shorter than the length specified for the output records, the standard output writer left-justifies the input record and pads the field with blanks.

When the output record length is variable and the input record length is fixed, the standard output writer adds control character information (if necessary) and variable record control information to the output record. Control character information is one byte, and record control information is four bytes long. Both additions are at the high-order end of the record.

If the output record is not at least 18 bytes long, the standard output writer pads it on the right with blanks. The standard output writer also adjusts the length of the output record to match the length of the output buffer.

4. When the output writing routine has successfully adjusted the input and output records, it can read the input data set until end of data. At that point, you need to consider another aspect of input data set processing: what is going to happen to the last input record?

The standard output writer handles output to either card punch or printer, as required; your routine could also send output to an intermediate tape or DASD device. Depending upon the kind of device, the last few records obtained from the input data set will receive different treatment.

It might happen that all the records from a given data set are not available on the output device until the output of records from the next data set is started, or until the output data set is closed. However, if you specify CERTIFY=Y as a start-up parameter, the records can be made available on the output device after all the input records have been written by the output writing routine. When the output data set is closed, the standard output writer automatically puts out the last record of its last input data set.

**For Punch Output:** When a card punch is the output device, the last three output cards could still be in the machine when the input data set is closed.

To put out these three records with the rest of the data set, and with no breaks, the standard output writer provides for three blank records following the actual data set records.

**For Printer Output:** When a printer is the output device, the last record of the input data set is not normally put in the output data set at the time the input data set is closed.

To force out this last record, the standard output writer generates a blank record to follow the last record of the actual data set.

- **Using the CERTIFY Function:** The CERTIFY function can be specified as a parameter when starting the external writer. It guarantees that data will not be lost when an abend condition occurs. If the CERTIFY function is not enabled, it is possible that records written to the QSAM buffers, but not yet written to the output device, can be purged before they are recorded during an abend situation.

This is possible, for example, when the output data set is not large enough to contain the data, resulting in an 'end-of-volume' (x37) abend.

The CERTIFY function flushes the buffers each time an input data set is processed, and makes that data available on the output device. However, while guaranteeing data integrity, this function might also increase processing overhead and decrease efficient output data set space utilization. Also, note that even with CERTIFY=Y, data integrity might be compromised in the case of writing multiple JES data sets to a partitioned dataset (PDS) or PDSE in an abend situation.

If you need to use the CERTIFY function, you need to modify your output writing routine to be similar to that supplied by IBM. Refer to module IEFSD087 for an example of how to enable the CERTIFY function. Basically, you must do the following:

1. In the external writer main task, force the number of buffers for the output data set to 1. That is, set DCBBUFNO=1.
  2. In the output writing routine after all records are PUT to the data set, perform a second PUT to write a blank line (a 'transition record') after the data to separate the data sets.
  3. In the output writing routine, commit the data to the output device.
- **Closing Input Data Set(s):** After the standard output writer finishes putting out the records of an input data set, it closes the data set before returning control to the calling module. All input data sets must be closed.

After closing the input data set, it is recommended that your output writer free the buffer pool associated with the input data set (by issuing the FREEPOOL macro).

- **Releasing Main Storage:** The output writing routine should release the storage it acquired, using the FREEMAIN or STORAGE macro, before returning to its caller.
- **Handling Errors:** The routine must put a return code into register 15 before returning to its caller using the RETURN macro.

The standard output writer sets a return code of 8 if it terminates because of an unrecoverable error on the output data set; otherwise, the return code is 0. The output writing routine must handle input errors itself.

## How the IBM-Supplied Output Separator Routine Works

The second major part of the IBM-supplied external writer routine is the output separator routine. Any output processing to a punch or printer must include a means of separating one job from another within the continuous deck or listing. When you specify IEFSD094 on the PARM= parameter on the EXEC card of the external writer, the IBM-supplied output separator routine writes separation records to the output data set prior to the writing of each job's output.

You can modify this separator routine to suit your installation's needs, or you can create your own routine. IBM's version does the following:

- **For Punch-Destined Output:** The separator routine provides three specially-punched cards (deposited in stacker 1) prior to the punch card output of each job. Each of these cards is punched in the following format:
  - Columns 1 to 35**  
blanks
  - Columns 36 to 43**  
job name
  - Columns 44 to 45**  
blanks
  - Column 46**  
output classname

## Columns 47 to 80

blanks

- **For Printer-Destined Output:** The IBM-supplied separator routine provides three specially-printed pages prior to printing the output of each job. Each of these separator pages is printed in the following format:
  - Beginning at the channel 1 location (normally near the top of the page), the job name is printed in block characters over 12 consecutive lines. The first block character of the 8-character job name begins in column 11. Each block character is separated by 2 blank columns.
  - The next two lines are blank.
  - The output classname is printed in block characters covering the next 12 lines. This is a 1-character name, and the block character begins in column 35.
  - The remaining lines, to the bottom of the page, are blank.
  - In addition to the block characters, a full line of asterisks (\*) is printed twice (that is, overprinted) across the folds of the paper. These lines are printed on the fold *preceding* each of the three separator pages, and on the fold *following* the third page. This is to make it easy for the operator to separate the job output in a stack of printed pages.

To control the location of the lines of asterisks on the page, the IBM-supplied separator routine requires that a channel 9 punch be included (along with the channel 1 punch) on the carriage control tape or in the forms control buffer (FCB). The channel 9 punch should correspond to the bottom of the page. The printer registration should be offset to print the line of asterisks on the fold of the page.

The IBM-supplied separator routine makes no provision for the 3800 printing subsystem; if you use it on a 3800, the FCB must locate a channel 9 punch at least one-half inch from the paper perforation.

**Separator Routine Parameter List:** IBM's external writer provides its separator routine with a 7-word parameter list of necessary information. When the separator routine receives control, register 1 contains the address of the parameter list, which contains the following:

Table 81. Separator Routine Parameter List

| Byte | Meaning                                                                                                |
|------|--------------------------------------------------------------------------------------------------------|
| 0    | Used to describe the type of output device                                                             |
|      | <b>Bit      Meaning</b>                                                                                |
|      | <b>011. ....</b> 2540 punch unit                                                                       |
|      | <b>001. ....</b><br>1403, 3203-5, 3211, or 3800 printer device                                         |
|      | <b>010. ....</b><br>tape device with punch-destined output                                             |
|      | <b>000. ....</b><br>tape device with printer-destined output                                           |
| 1-3  | Not used, but must be present                                                                          |
| 4-7  | Address of the DCB for the opened output data set where the external writer will put the input records |
| 8-11 | Address of an 8-character field containing the job name                                                |

Table 81. Separator Routine Parameter List (continued)

| Byte  | Meaning                                                         |
|-------|-----------------------------------------------------------------|
| 12-15 | Address of a 1-character field containing the output class name |
| 16-19 | Address of the data set PROC name in the SSOB extension.        |
| 20-23 | Address of the data set STEP name in the SSOB extension.        |
| 24-27 | Address of the data set DD name in the SSOB extension.          |

The parameter list points to a DCB; this DCB is established for the QSAM output data set, which is already open when the separator program receives control.

The address of the job name and the address of the output classname are provided in the parameter list so they can be used in the separation records the separator routine writes.

**Output from the Separator Routine:** A separator routine can write any kind of separation identification. IBM supplies a routine that constructs block characters. (See “Using the Block Character Routine” on page 409.) The separator routine can punch as many separator cards, or print as many separator pages, as necessary.

The output from the separator program must conform to the attributes of the output data set. To find out what these attributes are, examine the open output DCB pointed to by the parameter list. The attributes are:

- Record format (fixed, variable, or undefined length)
- Record length
- Type of carriage control characters (machine, ANSI, or none)

For printer-destined output, a separator routine can begin its separator records on the same page as the previous job output, or skip to any subsequent page. However, the separator routine should skip at least one line before writing any records because in some cases the printer is still positioned on the line last printed.

After completing the output of the separation records, the separator routine should write sufficient blank records to force out the last separation record. This also allows the error exit routine to obtain control if an uncorrectable output error occurs while writing the last record. One blank record, for printer-destined output, and three blank records, for punch-destined output, are sufficient to force out the last record.

**How to Add Your Own Output Separator Routine:** If you write your own separator routine, it must conform to the following requirements:

- The routine must have a unique name and this name must be specified in the PARM= parameter on the EXEC card for the external writer. If you do not specify the name of an output separator routine, no separator records are written.

**Note:** Do not use *CERTIFY* as the name of your output separator routine. Refer to “The EXEC Statement” on page 396 for details on specifying an output separator routine on the PARM= parameter.

- If you want to replace the standard IBM routine, then name your routine IEFSD094. This should reside in SYS1.LINKLIB or in a library concatenated to LINKLIB through a LNKSTxx member of SYS1.PARMLIB.
- The routine must use standard entry and exit linkages, saving and restoring its caller’s registers, and returning to its caller through the RETURN macro, with a return code in register 15.
- The routine must use the QSAM PUT macro in locate mode to write separation records to the output data set.

- The routine must use the GETMAIN and FREEMAIN macros, or the STORAGE macro, to obtain and release the storage required for work areas.
- The routine must establish its own synchronous error exit routine, and place the exit address in the DCBSYNAD field of the output DCB. The error routine will receive control during output writing in case of an uncorrectable I/O error; it must set a return code of 8 (binary) in register 15 to indicate an unrecoverable output error.

If the separator routine completes processing successfully, it must set a return code of 0 in register 15, before returning to its caller.

**Note:** The separator routine receives control in problem-program state, but with a protection key of 0. Therefore, the routine must ensure data protection during its execution.

**Using the Block Character Routine:** For printer-destined output, the separator routine can use an IBM-supplied routine to construct separation records in a block character format. This routine is a reentrant module named IEFSD095 that resides in the module library SYS1.AOSB0.

The block character routine constructs block letters (A to Z), block numbers (0 to 9), and a blank. The separator routine furnishes the desired character string and the construction area. The block characters are constructed one line position at a time. Each complete character is contained in 12 lines and 12 columns; therefore, a block character area consists of 144 print positions. For each position, the routine provides either a space or the character itself.

The routine spaces 2 columns between each block character in the string. However, the routine does not enter blanks between or within the block characters. The separator routine must prepare the construction area with blanks or other desired background before entering the block character routine.

To invoke the IBM-supplied block character routine, the IBM-supplied separator routine executes the CALL macro with the entry point name of IEFSD095. Since the block characters are constructed one line position at a time, complete construction of a block character string requires 12 entries to the routine. Each time, the address of a 7-word parameter list is provided in register 1.

The parameter list contains the following:

*Table 82. Block Character Routine Parameter List*

| Byte  | Meaning                                                                                                                                                                                                                                             |
|-------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| 0-3   | This fullword is the address of a field containing the desired character string in EBCDIC format.                                                                                                                                                   |
| 4-7   | This fullword is the address of a field containing the line count as a binary integer from 1 to 12. This represents the line position to be constructed on this call.                                                                               |
| 8-11  | This word is the address of a construction area where the routine will build a line of the block character string. The required length in bytes of this construction area is $14n-2$ , where $n$ represents the number of characters in the string. |
| 12-15 | This word is the address of a fullword field containing, in binary, the number of characters in the string.                                                                                                                                         |
| 16-19 | Address of the data set PROC name in the SSOB extension.                                                                                                                                                                                            |
| 20-23 | Address of the data set STEP name in the SSOB extension.                                                                                                                                                                                            |
| 24-27 | Address of the data set DD name in the SSOB extension.                                                                                                                                                                                              |





---

## Appendix D. Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:**

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs

and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Mail Station P300  
2455 South Road  
Poughkeepsie, NY 12601-5400  
USA

Such information may be available, subject to appropriate terms and condition including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

---

## Programming Interface Information

This book documents information that is not intended to be used as a programming interface of the JES2 element of z/OS.

---

## Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, or other countries, or both:

- ACF/VTAM
- Advanced Function Presentation
- Advanced Function Printing
- AFP
- AS/400
- AT
- CICS
- DFSMS/MVS

- DFSMSdfp
- ES/3090
- ES/9000
- ESCON
- IBM
- IBMLink
- IMS
- MVS
- MVS/DFP
- MVS/ESA
- OS/390
- System/370
- PERSONAL SYSTEM/2
- PR/SM
- Print Services Facility
- PS/2
- PSF
- DB2
- Sysplex Timer
- RACF
- Resource Link
- RETAIN
- RMF
- RT
- S/370
- SP
- SYSTEM/390
- VTAM
- XT
- 3090
- z/OS

Other company, product, and service names may be trademarks and service marks of others.



---

# Glossary

This glossary defines technical terms and abbreviations used in JES2 documentation. If you do not find the term you are looking for, refer to the index of the appropriate JES2 manual or view *IBM Glossary of Computing Terms*, available from:

[www.ibm.com/ibm/terminology](http://www.ibm.com/ibm/terminology)

This glossary includes terms and definitions from:

*American National Standard Dictionary for Information Systems*, ANSI X3.172-1990, copyright 1990 by the American National Standards Institute (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42nd Street, New York, New York 10036. Definitions are identified by an asterisk (\*) that appears between the term and the beginning of the definition; a single definition taken from ANSI is identified by an asterisk after the item number for that definition.

## A

**ACB.** Access control block

**ACF.** Advanced communication function

**address space.** The complete range of addresses available to a program. See also *virtual address space*.

**affinity.** The condition under which one or more members of a JES2 multi-access spool configuration may be designated as qualified to execute certain jobs.

**AFP.** Advanced function printing

**all-member warm start.** A JES2 member restart of the first member in a multi-access spool (MAS) configuration. Either the JES2 member previously ended without error or there must be an IPL of the MVS system.

**allocate.** To assign a resource for use in performing a specific task.

**APAR.** Authorized program analysis report

**APPC.** Advanced Program-to-Program Communication.

**APT.** Application table

**artificial JQE.** An artificial JQE consists of the base JQE, the JQX, and additional fields defined in the JQA.

**automatic restart.** A restart that takes place during the current run, that is, without resubmitting the job. An automatic restart can occur within a job step or at the beginning of a job step. Contrast with *deferred restart*. See also *checkpoint restart*.

**automatic volume recognition (AVR).** A feature that allows the operator to mount labeled volumes on available I/O devices before the volumes are needed by a job step.

**AVR.** Automatic volume recognition

## B

**background.** (1) In multiprogramming, the environment in which low-priority programs are executed. (2) Under TSO/E the environment in which jobs submitted through the SUBMIT command or SYSIN are executed. One job step at a time is assigned to a region of central storage, and it remains in central storage to completion. Contrast with *foreground*.

**background job.** (1) A low-priority job, usually a batched or non-interactive job. (2) Under TSO, a job entered through the SUBMIT command or through SYSIN. Contrast with *foreground job*.

**BAL.** Basic assembler language

**batch processing.** (1) \*Pertaining to the technique of executing a set of computer programs such that each is completed before the next program of the set is started. (2) \*Pertaining to the sequential input of computer programs or data. (3) \*Loosely, the serial execution of computer programs. (4) Under TSO, the processing of one job step in a region, so called because jobs are submitted in a group or batch.

**baud.** (1) A unit of signaling speed equal to the number of discrete conditions or signal events per second. For example, one baud equals one-half dot cycle per second in Morse code, one bit per second in a train of binary signals, and one 3-bit value per second in a train of signals each of which can assume one of eight different states. (2) In asynchronous transmission, the unit of modulation rate corresponding to one unit interval per second; that is, if the duration of the unit interval is 20 milliseconds, the modulation rate is 50 baud.

**binary synchronous communication (BSC).** Communication using binary synchronous transmission.

**binary synchronous transmission.** Data transmission in which synchronization of characters is controlled by timing signals generated at the sending and receiving stations.

**bind.** In SNA products, a request to activate a session between two logical units.

**broadcast data set.** Under TSO, a system data set containing messages and notices from the system operator, administrators, and other users. Its contents are displayed to each terminal user when he logs on the system, unless suppressed by the user.

**BSAM.** Basic sequential access method

**BSC.** Binary synchronous communication

**BSCA.** Binary synchronous communication adapter

**burst.** \*To separate continuous-form paper into discrete sheets.

## C

**cataloged data set.** A data set that is represented in an index or hierarchy of indexes that provide the means for locating it.

**cataloged procedure.** A set of job control statements that has been placed in a library and that can be retrieved by name.

**CCW.** Channel command word

**central storage.** (1) In System/390 virtual storage systems, the storage of a System/390 computing system from which the central processing unit can directly obtain instructions and data, and to which it can directly return results. (Formerly referred to as "real storage".) (2) Synonymous with *processor storage*.

**centralized control.** Control in which all the primary station functions of the data link are centralized in one data station. Contrast with *independent control*.

**CES.** Connection event sequence

**chain printer.** An impact printer that has a revolving chain with links that carry the type slugs.

**change log.** Area of the checkpoint data set that contains the specific control blocks changed by the last member of the multi-access spool configuration to own the checkpoint data set.

**channel-to-channel (CTC).** A method of connecting two computing devices.

**channel-to-channel (CTC) adapter.** A device for connecting two channels on the same processor or on different processors.

**checkpoint.** (1) \*A place in a routine where a check, or a recording of data for restart purposes, is performed. (2) A point at which information about the status of a job and the system can be recorded so that the job step

can be later started. (3) To record information about the status of a job and the system for restart purposes.

**checkpoint data set.** A data set in which information about the status of a job and the system can be recorded so that the job step can be restarted later.

**checkpoint reconfiguration.** A process used by JES2 to dynamically redefine checkpoint data set specifications for a JES2 MAS.

**checkpoint reconfiguration dialog.** An interactive form of a JES2 checkpoint reconfiguration where the operator directs the reconfiguration process with replies to a series of WTOR messages.

**checkpoint restart.** The process of resuming a job at a checkpoint within the job step that caused abnormal termination. The restart may be automatic or deferred, where deferred restart involves resubmitting the job. See also *automatic restart*; *deferred restart*. Contrast with *step restart*.

**checkpoint write.** Any write to the checkpoint data set. A general term for the primary, intermediate, and final writes that update any checkpoint data set.

**checkpoint/restart facility.** (1) A facility for restarting execution of a program at some point other than at the beginning, after the program was terminated due to a program or system failure. A restart can begin at a checkpoint or from the beginning of a job step, and uses checkpoint records to reinitialize the system. (2) Under TCAM, a facility that records the status of the teleprocessing network at designated intervals or following certain events. Following system failure, the system can be restarted and continue without loss of messages.

**checkpointing.** Preserving processing information during a program's operation that allows such processing to be restarted and duplicated.

**CKPT1.** The checkpoint data set designed as the one on which the reserve is acquired. In a DUAL mode configuration, CKPT1 is one of the alternately used primary data sets from which JES2 reads and writes the checkpoint. In a DUPLEX mode configuration, CKPT1 is the primary checkpoint data set.

**CKPT2.** In a DUAL mode configuration, CKPT2 is one of the alternately-used checkpoint data sets from which JES2 reads and writes the checkpoint. In a DUPLEX mode configuration, CKPT2 is the back-up copy (generally down-level) of the primary checkpoint data set (CKPT1) which can be used to replace CKPT1 if necessary. CKPT2 is formatted the same as CKPT1. (Previously CKPT2 was the DUPLEX checkpoint data set).

**CLPA.** Common link pack area

**CMB.** Console message buffer

**CMS.** Cross memory services

**cold start.** A JES2 member start that initializes data areas and accounting information in central storage and the job and output queues.

**communication line.** Any physical link, such as a wire or telephone circuit, for connecting geographically dispersed computer systems.

**complex.** The maximum set of hardware and software resources that support one or more images of a single operating system.

**configuration.** The arrangement of a computer system or network as defined by the nature, number, and chief characteristics of its functional units.

**connection event sequence.** A clock value that indicates the time a connection took place or was broken. This is copied to NCC records and used by the path manager to determine the “most current” record when keeping track of NJE connections.

**console.** Any device from which operators can enter commands or receive messages. For JES2, the same device from which an operator also enters MVS base control program commands.

**control statements.** Statements placed into an input stream to identify special JES2 processing options for jobs.

**CSA.** Common service area

**CSECT.** Control section

**CTC.** Channel-to-channel adapter

## D

**DASD.** Direct access storage device

**data integrity point.** The generic name given to the point in the 3800 model 3 printing process at which the data is known to be secure. (Also called the stacker.)

**data set forwarding.** The dynamic replacement of the checkpoint data set specifications (data set name and volume) with new specifications.

**data set separator pages.** Those pages of printed output that delimit data sets.

**DCT.** Device control table

**deallocate.** To release a resource that is assigned to a specific task.

**dedicated.** Pertaining to the assignment of a system resource - a device, a program, or a whole system - to an application or purpose.

**deferred restart.** A restart performed by the system when a user resubmits a job. The operator submits the restart deck to the system through a system input reader. See also *checkpoint restart*. Contrast with *automatic restart*.

**dependent job control (DJC).** A method of handling multiple jobs that must be run in a specific order because of job dependencies.

**despooling.** The process of reading records off the spool into central storage. During the despooling process, the physical track addresses of the spool records are determined.

**destination.** A combination of a node name and one of the following: a userid, a remote printer or punch, a special local printer, or LOCAL (the default if only a node name is specified).

**destination identifier (destid).** The 8-character subscript on the DESTID(jxxxxxx) initialization statement or command that corresponds to a combination of a first-level destination and a second-level destination that determines where data should be sent in a JES2 installation. A destid can be either a symbolic destination or an explicit destination.

**destination node.** Node to which data is sent.

**device partitioning.** A pool of devices (called a fence) to be used exclusively by a set of jobs in a specific job class allowing an installation to tailor its device usage to its anticipated workload.

**direct access storage device (DASD).** A device in which the access time is effectively independent of the location of the data.

**DJC.** Dependent job control.

**DUAL mode.** A checkpointing mode that provides the alternate use of two primary checkpoint data sets (CKPT1 and CKPT2). The data sets are referred to as the to-be-read-from and to-be-written-to data sets.

**dump.** A report showing the contents of storage. Dumps are typically produced following program failures, for use as diagnostic aids.

**DUPLEX mode.** A checkpointing mode that provides the continuous use of only one checkpoint data set. A second (backup) data set is defined, but it is written to less frequently than the primary.

**dynamic allocation.** Assignment of system resources to a program at the time the program is executed rather than at the time it is loaded into central storage.

**dynamic connection.** A connection created via sign-on or NCC record sent from another node. Synonymous with *non-static connection*.



**dynamic table.** An installation-defined table that is used to extend, modify, or delete the JES2 default processing specifications. See also *table pair*.

## E

**EBCDIC.** Extended binary coded decimal interchange code

**ECSA.** Extended common service area

**EM.** End of media

**end of block (EOB).** A code that marks the end of a block of data.

**end-of-file mark (EOF).** A code that signals that the last record of a file has been read.

**EOB.** End of block

**EOF.** End of file

**EPVT.** Extended private storage area

**execution node.** The JES2 network job entry node upon which a job is to be executed.

**exit points.** The place in the code where a routine (exit) receives control from the system.

**explicit destination.** A destination identifier of the form Nnnnn, Rmmmm, RMmmmm, RMTmmmm, NnnnnRmmmm or Unnnn. See also *destination identifier* and *symbolic destination*.

**extended binary coded decimal interchange code (EBCDIC).** A set of 256 characters, each represented by 8 bits.

**external writer.** A program that supports the ability to write SYSOUT data in ways and to devices not supported by the job entry subsystem.

## F

**facility.** (1) A feature of an operating system, designed to service a particular purpose, for example, the checkpoint/restart facility. (2) A measure of how easy it is to use a data processing system. Together with system performance, a major factor on which the total productivity of an installation depends. (3) Anything used or available for use in furnishing communication service. Commonly, a general term for communications paths.

**FCB.** Forms control buffer

**final write.** A write of the same information as the intermediate write done at the end of the checkpoint cycle. See also *intermediate write*.

**first-level destination.** The nodal portion of a destination (the node to which the data goes).

**foreground.** (1) in multiprogramming, the environment in which high-priority programs are executed. (2) Under TSO, the environment in which programs are swapped in and out of central storage to allow CPU time to be shared among terminal users. All command processor programs execute in the foreground. Contrast with *background*.

**foreground job.** (1) A high-priority job, usually a real-time job. (2) A teleprocessing or graphic display job that has an indefinite running time during which communication is established with one or more users at local or remote terminals. (3) Under TSO, any job executing in a swapped region of central storage, such as a command processor or a terminal user's program. Contrast with *background job*.

**forms control buffer (FCB).** A buffer that is used to store vertical formatting information for printing; each position corresponding to a line on the form.

**forwarding.** The dynamic replacement of the checkpoint data set specifications (data set name and volume) with new specifications.

**FSA.** Functional subsystem application

**FSA startup.** That part of system initialization when the FSA is loaded into the functional subsystem address space and begins initializing itself.

**FSI.** Functional subsystem interface

**FSI connect.** The FSI communication service which establishes communication between JES2 and the FSA or functional subsystem.

**FSI disconnect.** The FSI communication service which severs the communication between JES2 and the FSA or functional subsystem.

**FSI services.** A collection of services available to users (JES2) of the FSI. These services comprise communication services, data set services, and control services.

**FSS.** Functional subsystem

**full-function mode.** The state that permits a printer to produce page-mode output.

**functional subsystem (FSS).** An address space uniquely identified as performing a specific function related to the JES. For JES2, an example of an FSS is the Print Services Facility program that operates the 3800 Model 3 and 3820 printers.

**functional subsystem application (FSA).** The functional application program managed by the functional subsystem.

**functional subsystem interface (FSI).** The interface through which JES2 or JES3 communicate with the functional subsystem.

**functional subsystem startup.** That process part of system initialization when the functional subsystem address space is created.

## G

**global command.** A command that is recognized and honored by any node in a JES2 network.

**global processor.** In JES3, the processor that controls job scheduling and device allocation for a complex of processors.

**GMT.** Greenwich mean time.

**Greenwich mean time (GMT).** The mean solar time of the meridian of Greenwich used as the prime basis of standard time throughout the world. See also *TOD clock*.

## H

**handshaking.** Exchange of predetermined signals when a connection is established between two data set devices.

**HASP.** Houston automatic spooling priority. A computer program that provides supplementary job management, data management, and task management functions, such as: control of job flow, ordering of tasks, and spooling. See also *JES2*.

**HASP table.** See *JES2 table*.

**HCT.** HASP communication table

**host processor.** (1) \*In a network, the processing unit in which resides the access method for that network. (2) In an SNA network, the processing unit that contains a system services control point (SSCP).

**host system.** \*The data processing system to which a network is connected and with which the system can communicate.

**host-id.** The unique 10-digit CPU identification made up of the 6-digit CPU serial number followed by a 4-digit model number.

**hot start.** A JES2 member restart performed when a member ends abnormally and the MVS system is not re-IPLed.

## I

**I/O.** input/output

**IBM-defined exit.** The point in source code where IBM has added an exit point where an installation routine can receive control from the operating system. Contrast with *installation-defined exit*.

**impact printer.** \*A printer in which printing results from mechanical impacts.

**independent control.** In JES2, the process by which each processor in a complex controls its own job input, scheduling, and job output. Contrast with *centralized control*.

**independent mode.** A means of isolating a processor for testing purposes. A processor so designated will only process jobs that are both routed to it and are themselves designated to execute on a processor in independent mode.

**initial program load (IPL).** The initialization procedure that causes an operating system to commence operation.

**initialization data set.** The data set that contains the initialization statements and their parameters that controls the initialization and ultimate processing of JES2.

**initialization parameter.** An installation-specified parameter that controls the initialization and ultimate operation of JES2.

**initialization statement.** An installation-specified statement that controls the initialization and ultimate operation of JES2.

**initiating task.** The job management task that controls the selection of a job and the preparation of the steps of that job for execution.

**initiator.** That part of an operating system that reads and processes operation control language statements from the system input device.

**initiator/terminator.** The job scheduler function that selects jobs and job steps to be executed, allocates input/output devices for them, places them under task control, and at completion of the job, supplies control information for writing job output on a system output unit.

**input service processing.** In JES2, the process of performing the following for each job: reading the input data, building the system input data set, and building control table entries.

**input stream control.** Synonymous with *JES2 reader*.

**installation-defined exit.** The point in source code where an installation adds an exit point where an installation routine can receive control from the operating system. Contrast with *IBM-defined exit*.

**interface.** Hardware, software, or both, that links systems, programs, or devices.

**intermediate write.** In DUAL mode, the write of the change log records containing the control blocks that have been updated since the last checkpoint write. In DUPLEX mode (or DUAL mode where the change log overflows the first track) the checkpoint write of the 4K records.

**internal reader.** A facility that transfers jobs to JES.

**interrupt.** (1) \*To stop a process in such a way that it can be resumed. (2) In data transmission, to take an action at a receiving station that causes the transmitting station to terminate a transmission.

**IOT.** input/output table

**IPL.** initial program load

**IPS.** Installation performance specification

## J

**JCL.** Job control language

**JCT.** Job control table

**JES2.** Job entry subsystem 2. An MVS subsystem that receives jobs into the system, converts them to internal format, selects them for execution, processes their output, and purges them from the system. In an installation with more than one processor, each processor's JES2 subsystem independently controls job input, scheduling, and output processing.

**JES2 reader.** In MVS, the part of the job entry subsystem that controls the input stream and its associated job control statements. Synonymous with *input stream control*.

**JES2 table.** A JES2-defined table that is used to specify the default characteristics of many of its initialization parameters, commands, and other externals. See also *table pair*.

**JES2 writer.** In MVS, the part of the job entry subsystem that controls the output of specified data sets. Synonymous with *output stream control*.

**JES3.** Job entry subsystem 3. An MVS subsystem that receives jobs into the system, converts them to internal format, selects them for execution, processes their output, and purges them from the system. In an installation with multiple processors (a JES3 complex), one processor's JES3 subsystem exercises centralized control over the other processors and distributes jobs to them through use of a common job queue.

**JIX.** Job queue index

**JMR.** Job management record

**job.** A unit of work for an operating system. Jobs are defined by JCL statements.

**job class.** Any one of a number of job categories that can be defined. With the classification of jobs and direction of initiator/terminators to initiate specific classes of jobs, it is possible to control the mixture of jobs that are performed concurrently.

**job control language (JCL).** A programming language used to code job control statements.

**job control language (JCL) statements.** Statements placed into an input stream to define work to be done, methods to be used, and the resources needed.

**job control statement.** \*A statement in a job that is used in identifying the job or describing its requirements to the operating system.

**job entry subsystem (JES).** An MVS facility that receives jobs into the system and processes output data produced by the jobs. See also *JES2* and *JES3*.

**job entry subsystem 2.** See *JES2*.

**job entry subsystem 3.** See *JES3*.

**job output element (JOE).** Information that describes a unit of work for the output processor and represents that unit of work for queuing purposes.

**job priority.** A value assigned to a job that is used as a measure of the job's relative importance while the job contends with other jobs for system resources.

**job queue element (JQE).** A control block that represents an element of work for the system (job) and is moved from queue to queue as that work moves through each successive stage of JES2 processing.

**job separator page data area (JSPA).** A data area that contains job-level information for a data set. This information is used to generate job header, job trailer or data set header pages. The JSPA can be used by an installation-defined JES2 exit routine to duplicate the information currently in the JES2 separator page exit routine.

**job separator pages.** Those pages of printed output that delimit jobs.

**JOE.** Job output element

**JOT.** Job output table

## K

**keyword.** A part of a command operand that consists of a specific character string (such as *DSNAME=*).

**keyword parameter.** A parameter that consists of a keyword, followed by one or more values. Contrast with *positional parameter*. See also *parameter*.

## L

**label.** (1) \*One or more characters used to identify a statement or an item of data in a computer program. (2) An identification record for a tape or disk file.

**line mode.** A type of data with format controls that only allow a printer to format data as a line.

**line-mode data.** A type of data that is formatted on a physical page by a printer only as a single line.

**LMT.** Load module table

**local devices.** Those devices that are directly attached to the operating system without the need for transmission facilities.

**local processing environment.** The collection of devices all of which are locally attached. That is, they are connected without the need for transmission facilities.

**local system queue area (LSQA).** In MVS, one or more segments associated with each virtual storage region that contain job-related system control blocks.

**locally attached.** A manner of device connection without the need for transmission facilities.

**logical unit (LU).** The combination of programming and hardware of a teleprocessing subsystem that functions like a terminal to VTAM.

**logoff.** (1) The procedure by which a user ends a terminal session. (2) In VTAM, a request that a terminal be disconnected from a VTAM application program.

**logon.** (1) The procedure by which a user begins a terminal session. (2) In VTAM, a request that a terminal be connected to a VTAM application program.

**loop.** A situation in which an instruction or a group of instructions execute repeatedly.

**LPA.** Link pack area

**LTRECL.** Logical record length

**LSQA.** Local system queue area

**LU.** Logical unit

## M

**machine check interruption.** An interruption that occurs as a result of an equipment malfunction or error.

**MAS.** See *multi-access spool configuration*.

**MCS.** Multiple console support

**member.** A JES2 instance of a MVS system

**message.** For communication lines, a combination of characters and symbols transmitted from one point to another. See also *operator message*.

**MIT.** Module information table

**MLU.** Multiple logical unit

**multi-access spool complex.** See *multi-access spool configuration*.

**multi-access spool configuration.** Multiple systems sharing the JES2 input, job and output queues (via a checkpoint data set or coupling facility).

**multi-access spool multiprocessing.** Two or more computing systems interconnected by an I/O channel-to-channel adapter. The CPs can be different types and have their own unique configurations.

**multiple console support (MCS).** A feature of MVS that permits selective message routing to up to 32 operator's consoles.

**Multiple Virtual Storage (MVS).** An operating system that manages resources and work flow while jobs are running.

**multiprocessing.** (1) \*Pertaining to the simultaneous execution of two or more computer programs or sequences of instructions by a computer network. (2) \*Loosely, parallel processing. (3) Simultaneous execution of two or more sequences of instructions by a multiprocessor.

**multiprocessing system.** A computing system employing two or more interconnected processing units to execute programs simultaneously.

**multiprocessor.** (1) A computer employing two or more processing units under integrated control. (2) A system consisting of two or more CPs (or ALUs, or processors) that can communicate without manual intervention.

**MVS.** Multiple virtual storage.

## N

**NACT.** Network account table

**NAT.** The nodes attached table, which is an internal JES2 control block containing information about each pair of nodes connected, or recently disconnected.

**NCC record.** The network connection and control records.

**NCP.** Network control program

**NCP/VS.** Network control program/VS

**NDH.** Network data set header

**network.** For JES2, two or more systems and the connections over which jobs and data are distributed to the systems. The other systems can be non-JES2 systems with compatible networking facilities. Connections can be established through communications paths using SNA or BSC protocols.

**network job entry (NJE).** A JES2 facility that provides for the passing of selected jobs, system output data, operator commands, and messages between communicating job entry subsystems connected by binary-synchronous communication lines, channel-to-channel adapters, and shared queues.

**Network Job Entry (NJE) facility.** In JES2, a facility which provides for the transmission of selected jobs, operator commands, messages, SYSOUT data, and accounting information between communicating job entry nodes that are connected in a network either by binary synchronous communication (BSC) lines channel-to-channel (CTC) adapters, or by System Network Architecture (SNA).

**Network Job Entry facility.** In JES2, a facility which provides for the transmission of selected jobs, operator commands, messages, SYSOUT data, and accounting information between communicating job entry nodes that are connected in a network either by binary synchronous communication (BSC) lines or by channel-to-channel (CTC) adapters.

**network operator.** (1) The person responsible for controlling the operation of a telecommunication network. (2) A VTAM application program authorized to issue network operator commands.

**NIP.** Nucleus initialization program.

**NIT.** The node information table, which is an internal JES2 control block containing information about each NJE node.

**NJE.** Network job entry

**NJH.** Network job header

**node.** (1) One of the systems in a network of systems connected by communication lines or CTC adapters. (2) In VTAM, an addressable point in a telecommunication system defined by a symbolic name. (3) In JES2 NJE, one or more job entry subsystems sharing a common job queue.

**node name.** An 8-character alphameric name which represents a node to other parts of the NJE network.

**non-impact printer.** \*A printer in which printing is not the result of mechanical impacts; for example, thermal printers, electrostatic printers, photographic printers.

**non-static connection.** A connection created via sign-on or NCC record sent from another node  
Synonymous with *dynamic connection*.

**nonpageable dynamic area.** \*In MVS, an area of virtual storage whose virtual addresses are identical to real addresses; it is used for programs or parts of programs that are not to be paged during execution. Synonymous with *V=R dynamic area*.

**nonpageable region.** In MVS, a subdivision of the nonpageable dynamic area that is allocated to a job step or system task that is not to be paged during execution. In a nonpageable region, each virtual address is identical to its real address. Synonymous with *V=R region*.

**nucleus.** That portion of a control program that always remains in central storage.

**nucleus initialization program (NIP).** The MVS component that initializes the resident control program.

## O

**offload.** Moving jobs and work off the work queues to remove them from contention for system resources, or off spool to free up system work space.

**operand.** (1) \*That which is operated upon. An operand is usually identified by an address part of an instruction. (2) Information entered with a command name to define the data on which a command processor operates and to control the execution of the command processor.

**operator commands.** Statements that system operators may use to get information, alter operations, initiate new operations, or end operations.

**operator message.** A message from an operating system directing the operator to perform a specific function, such as mounting a tape reel; or informing the operator of specific conditions within the system, such as an error condition.

**operator orientation point.** The generic name given to the point in the 3800 model 3 printing process at which the data becomes visible to the operator, and is therefore the point at which all operator commands are directed. Synonymous with *transfer station*.

**output group.** A set of a job's output data sets that share output characteristics, such as class, destination, and external writer.

**output stream control.** Synonymous with *JES2 writer*.

**output writer.** A part of the job scheduler that transcribes specified output data sets onto a system output device independently of the program that produced the data sets.



**overlays.** A collection of predefined data such as lines, shading, text, boxes, or logos, that can be merged with the variable data on a page while printing.

## P

**page.** (1) In virtual storage systems, a fixed-length block of instructions, data, or both, that can be transferred between central storage and external page storage. (2) To transfer instructions, data, or both, between central storage and external page storage. (3) The unit of output from a 3800-3 running with full function capability or 3820 printer.

**page data set.** In System/390 virtual storage systems, a data set in external page storage in which pages are stored.

**page fault.** In System/390 virtual storage systems, a program interruption that occurs when a page that is marked "not in central storage" is referred to by an active page.

**page mode.** The mode of operation in which the 3800 Printing Subsystem can accept a page of data from a host processor to be printed on an all-points-addressable output medium.

**page-mode data.** A type of data that can be formatted anywhere on a physical page. This data requires specialized processing such as provided by the Print Services Facility for the 3800-3 and 3820 printers.

**page-mode environment checkpointing.** That process which preserves the information necessary to resume page-mode printing.

**page-mode printer.** A printer (such as the 3800 model 3 and 3820) that can print page-mode data.

**pageable region.** In MVS, a subdivision of the pageable dynamic area that is allocated to a job step or a system task that can be paged during execution. Synonymous with *V=V region*.

**paging.** In System/390 virtual storage systems, the process of transferring pages between central storage and external page storage.

**paging device.** In System/390 virtual storage systems, a direct access storage device on which pages (and possibly other data) are stored.

**parameter.** (1) \*A variable that is given a constant value for a specific purpose or process. (2) See *keyword parameter*, *positional parameter*.

**password.** A unique string of characters that a program, computer operator, or user must supply to meet security requirements for gaining access to data.

**patch.** \*To modify a routine in a rough or expedient way.

**path.** In VTAM, the intervening nodes and lines connected a terminal and an application program in the host CPU.

**path manager.** The part of JES2 that controls NJE sign-on, sign-off, keeps track of all other nodes and connections in the network, and determines the best path to reach those nodes. (JES2 is unique among other NJE subsystems in keeping track of the network topology through NCC records.)

**PCE.** Processor control element

**PDDb.** Peripheral data definition block

**PEP.** Partitioned emulator program

**physical unit (PU).** (1) The control unit or cluster controller of an SNA terminal. (2) The part of the control unit or cluster controller that fulfills the role of a physical unit as defined by systems network architecture (SNA).

**PLPA.** Pageable link pack area

**poly-JES.** Concurrent operation of multiple copies of JES2 on a single MVS system to allow an installation to separate its primary production system(s) and test system(s).

**positional parameter.** A parameter that must appear in a specified location, relative to other parameters. Contrast with *keyword parameter*. See also *parameter*.

**PPL.** Purge parameter list

**PRE.** Processor recovery element

**primary write.** The write of the 4K records to the down-level checkpoint data set to make it current.

**Print Services Facility.** The program (code) that operates the 3800 model 3 and 3820 printers. The Print Services Facility operates as a functional subsystem.

**priority aging.** A function of JES2 by which the longer a job waits to be selected for processing, the greater become its chances of being selected to run.

**private connection.** A connection known only to the two nodes making the connection.

**process mode.** The mode in which SYSOUT data exists and is to be processed by a JES output device. There are two IBM-defined process modes: line mode and page mode.

**processor storage.** See *central storage*.

**program temporary fix (PTF).** A temporary solution or bypass for a problem diagnosed by IBM as the result of a defect in a current unaltered release of the program.

**protocols.** Rules for using communication lines. Protocols can identify the direction of data flow, where

data begins and ends, how much data is being transmitted, and whether data or control information is being sent.

**PSF.** Print Services Facility

**PTF.** Program temporary fix

**PU.** Physical unit.

## Q

**QSE.** Shared queue element

**queue.** A line or list formed by items in a system waiting for processing.

**quick start.** A JES2 member restart in an existing multi-access spool (MAS) configuration. The JES2 member previously ended without error.

**quiescing.** \*The process of bringing a device or a system to a halt by rejection of new requests for work.

## R

**RACF.** Resource Access Control Facility

**read 1.** A read of the first track of a checkpoint data set. Usually performed as the initial I/O operation to a checkpoint data set.

**read 2.** A read of the 4K page data records and any change log records not contained on the first track from a checkpoint data set. Usually performed after a READ 1 as the second checkpoint I/O operation in a checkpoint cycle.

**reader.** A program that reads jobs from an input device or data base file and places them on the job queue.

**real address.** In virtual storage systems, the address of a location in central storage.

**real storage.** See *central storage*.

**remote.** RMT

**remote job entry (RJE).** Submission of job control statements and data from a remote terminal, causing the jobs described to be scheduled and executed as though encountered in the input stream.

**remote station.** \*Data terminal equipment for communicating with a data processing system from a location that is time, space, or electrically distant.

**remote terminal.** An input/output control unit and one or more input/output devices attached to a system through a data link.

**remote terminal access method (RTAM).** A facility that controls operations between the job entry subsystem (JES2) and remote terminals.

**remote workstation.** (1) \*Data terminal equipment for communicating with a data processing system from a location that is time, space, or electrically distant. Synonymous with *remote station*. (2) A workstation that is connected to a system by means of data transmission facilities.

**RJE.** Remote job entry

**RMS.** Recovery management support

**RMT.** Remote

**RMT generation.** Generation of remote workstations for remote job entry.

**routing.** (1) The assignment of the communications path by which a message or telephone call will reach its destination. (2) In NJE, the path, as determined by NJE or explicitly by the operator, that a job or SYSOUT data set will take to reach its destination.

**routing code.** A code assigned to an operator message and used, in systems with multiple console support (MCS), to route the message to the proper console.

**RPL.** Request parameter list

**RPS.** Rotational position sensing

**RTAM.** Remote terminal access method

**RTP.** Remote terminal program

## S

**SAF.** Security authorization facility

**SAM.** Sequential access method

**SDLC.** Synchronous data link control

**SDSB.** Spool data set browse

**second-level destination.** Specifies a remote workstation, special local route code, userid, or LOCAL or ANYLOCAL (for data not associated with a specific routing).

**secondary console.** In a system with multiple consoles, any console except the master console. The secondary console handles one or more assigned functions on the multiple console system.

**security classification.** (1) An installation-defined level of security printed on the separator pages of printed output. (2) In RACF, the use of security categories, a security level, or both, to impose additional



access controls on sensitive resources. An alternative way to provide security classifications is to use security labels.

**segments.** A collection of composed text and images, prepared before formatting and included in a document when it is printed.

**session.** (1) The period of time during which a user of a terminal can communicate with an interactive system; usually, the elapsed time from when a terminal is logged on to the system until it is logged off the system. (2) The period of time during which programs or devices can communicate with each other. (3) In VTAM, the period of time during which a node is connected to an application program.

**setup.** The preparation of a computing system to perform a job or job step. Setup is usually performed by an operator and often involves performing routine functions, such as mounting tape reels and loading card decks.

**shared broadcasting.** The two TSO data sets SYS1.UADS (TSO user definition) and SYS1.BROADCAST (TSO message transmission definition) are shared by all systems in the multi-access spool (MAS) complex.

**simultaneous peripheral operations online (spool).** The reading and writing of input and output streams on auxiliary storage devices, concurrently while a job is running, in a format convenient for later processing or output operations.

**single-member warm start.** A JES2 member restart of a new member in an existing multi-access spool (MAS) configuration. The JES2 member previously ended abnormally. Before the restart can occur, there must be an IPL of the MVS system.

**single-processor complex.** A processing environment in which only one processor (computer) accesses the spool and comprises the entire node.

**SMF.** System management facilities

**SNA.** Systems Network Architecture

**special local.** A routing in the form Unnnn, where 'nnnn' signifies a numeric value in the range of 1–32767. Usually, installations use this routing to specify local printers and punches.

**spin data set.** A data set that is deallocated (available for printing) when it is closed. Spin off data set support is provided for output data sets just prior to the termination of the job that created the data set.

**spool.** Simultaneous peripheral operations online.

**spooled data set.** A data set written on an auxiliary storage device and managed by JES.

**spooled data set browse (SDSB).** An application that allows a program to read spool data sets.

**spooling.** The reading and writing of input and output streams on auxiliary storage devices, concurrently with job execution, in a format convenient for later processing or output operations.

**SQA.** System queue area

**SRM.** System resources manager

**static connection.** A connection (also called "predefined connection" in earlier releases) between two nodes created by either a JES2 initialization or an operator command.

**STC.** Started task control

**step restart.** A restart that begins at the beginning of a job step. The restart may be automatic or deferred, where deferral involves resubmitting the job. Contrast with *checkpoint restart*.

**subnet.** Subset of a NJE network identified by an eight-character 'SUBNET' name on the JES2 NODE initialization statement. The grouping of nodes into "SubNets" is based on the assumption that if you have access to any node in the subnet, you have access to them all.

**subsystem.** A secondary or subordinate system, usually capable of operating independently of, or asynchronously with, a controlling system.

**SVC.** Supervisor call instruction

**SVC interruption.** An interruption caused by the execution of a supervisor call instruction, causing control to be passed to the supervisor.

**SWA.** Scheduler work area

**swap data set.** A data set dedicated to the swapping operation.

**swapping.** An MVS paging operation that writes the active pages of a job to auxiliary storage and reads pages of another job from auxiliary storage into central storage.

**symbol.** (1) \*A representation of something by reason of relationship, association, or convention. (2) In MVS, a group of 1 to 8 characters, including alphanumeric characters and the three characters: #, @, \$. The symbol begins with either an alphabetic character or one of the three characters (#, @, \$).

**symbolic address.** \*An address expressed in symbols convenient to the computer programmer.

**symbolic destination.** A destination identifier specifying a symbolic name that represents a JES2 destination. See also *destination identifier* and *explicit destination*.

**synchronous data link control (SDLC).** A discipline for managing synchronous, transparent, serial-by-bit information transfer over a communication channel. Transmission exchanges may be duplex or half-duplex over switched or nonswitched data links. The communication channel configuration may be point-to-point, multipoint, or loop.

**syntax.** (1) \*The structure of expressions in a language. (2) The rules governing the structure of a language.

**SYSIN.** A system input stream; also, the name used as the data definition name of a data set in the input stream.

**SYSLOG.** System log

**SYSOUT.** A system output stream; also, an indicator used in data definition statements to signify that a data set is to be written on a system output unit.

**sysplex.** A set of MVS systems communicating and cooperating with each other through certain multisystem hardware components and software services to process customer workloads.

**system affinity.** See *affinity*.

**system control programming.** IBM-supplied programming that is fundamental to the operation and maintenance of the system. It serves as an interface with program products and user programs and is available without additional charge.

**system management facilities (SMF).** An MVS component that provides the means for gathering and recording information that can be used to evaluate system usage.

**system output writer.** A job scheduler function that transcribes specified output data sets onto a system output unit, independently of the program that produced the data sets.

**system queue area (SQA).** In MVS, an area of virtual storage reserved for system-related control blocks.

**system services control point.** \*In SNA, the focal point within an SNA network for managing the configuration, coordinating network operator and problem determination requests, and providing directory support and other session services for end users of the network.

**systems network architecture (SNA).** The total description of the logical structure, formats, protocols,

and operational sequences for transmitting information units through a communication system.

## T

**table pair.** A set of JES2-defined, USER-defined, and dynamic tables that an installation can use to modify JES2 processing.

**TCAM.** Telecommunications access method.

**telecommunications access method (TCAM).** A method used to transfer data between central storage and remote or local terminals. Application programs use either GET and PUT or READ and WRITE macro instructions to request the transfer of data, which is performed by a message control program. The message control program synchronizes the transfer, thus eliminating delays for terminal/output operations.

**teleprocessing.** The processing of data that is received from or sent to remote locations by way of telecommunication lines.

**terminal.** A device, usually equipped with a keyboard and some kind of display, capable of sending and receiving information over a communication channel.

**text transparency.** A provision that allows BSC to send and receive messages containing any or all of the 256 character combinations in EBCDIC, including transmission control characters. Transmission control characters sent in a message are treated as data unless they are preceded by the data link escape (DLE) control character.

**TGB.** Track group block

**TGBE.** Track group block entry

**tightly-coupled multiprocessing.** Two computing systems operating simultaneously under one control program while sharing resources.

**Time Sharing Option Extensions (TSO/E).** A licensed program that is based on the Time Sharing Option (TSO). It allows MVS users to interactively share computer time and resources.

**time tolerance.** The difference between the TOD clocks on two adjacent nodes, beyond which the path manager will not allow a session to be established.

**time-of-day clock.** See *TOD clock*.

**TOD.** Time-of-day

**TOD clock.** A timing device that counts units of time based on the starting point of 00 hours, 00 minutes, and 00 seconds on January 1, 1900. Time-of-day (TOD) information is used, for example, to monitor computer operations and events.

**token.** Specifically defined for JES2 checkpoint processing as a checkpoint identifier that is used to determine checkpoint I/O status.

**trace.** (1) The record of a series of events. (2) To record a series of a events as they occur. (3) A report showing data relevant to a particular point in the processing of a program. Traces are typically produced for analysis of program performance, but they can also be valuable diagnostic aids.

**tracing routine.** \*A routine that provides a historical record of specified events in the execution of a program.

**traffic.** In data communication, the quantity of data transmitted past a particular point in a path.

**train printer.** A printer in which the type slugs are assembled in a train that moves along a track. Contrast with *chain printer*.

**transfer station.** The point in the 3800 model 3 printing process at which the data set becomes visible to the operator, and is therefore the point at which all operator commands are directed. Synonymous with *operator orientation point*.

**TSO.** Time-sharing option. See *Time Sharing Option Extensions (TSO/E)*.

**TSO/E.** Time Sharing Option Extensions

**TSU.** Time-sharing user

**TTE.** Trace table entry

**type font.** In printing, a set of type that is of a particular size and style (for example, 10-point century school book).

## U

**UCB.** Unit control block

**UCS.** Universal character set.

**unallocate.** See *deallocate*.

**unit.** (1) \*A device having a special function. (2) A basic element.

**unit address.** The address of a particular device, specified at the time a system is installed; for example, 191 or 293.

**universal character set (UCS).** A printer feature that permits the use of a variety of character arrays.

**user identification (USERID).** A 1-8 character symbol identifying a system user.

**user table.** An installation-defined table that is used to extend, modify, or delete the JES2 default processing specifications. See also *table pair*.

**USERID.** User identification.

## V

**V=R dynamic area.** Synonymous with *nonpageable dynamic area*.

**V=R region.** Synonymous with *nonpageable region*.

**V=V region.** Synonymous with *pageable region*.

**VIO.** virtual input/output

**virtual address space.** In virtual storage systems, the virtual storage assigned to a job, terminal user, or system task. See also *address space*.

**Virtual Telecommunications Access Method (VTAM).** A set of programs that control communication between terminals and application programs running under MVS.

**VTAM.** Virtual Telecommunications Access Method.

## W

**warm start.** A general term for a JES2 member restart. See also *hot start*; *quick start*; *single-member warm start*; *all-member warm start*.

**writer.** See *output writer*.

**WTO.** Write-to-operator

**WTOR.** Write-to-operator with reply

## X

**XFER.** Transfer

**XIT.** Exit information table

**XRT.** Exit routine table

## Numerics

**3800 compatibility mode.** Operating the 3800 model 3 printer as a 3800 Model 1 printer.

**3800 model 3 startup.** That process part of system initialization when the 3800 model 3 printer is initializing.



---

# Index

## Special Characters

- /\*\$VS control statement
  - defining 101
- /\*JOBPARM control statement
  - member affinity 63
- /\*OUTPUT control statement
  - 3211 indexing 132
  - JESNEWS relation 138
  - output routing 142
  - RJE compaction 330
- /\*PRIORITY control statement 89
- /\*ROUTE control statement
  - system output routing 142
- /\*ROUTE XEQ control statement
  - define execution node 261
  - relation to network accounting 84
- /\*XEQ control statement
  - define execution node 261
  - network accounting 84
- /\*XMIT control statement
  - define execution node 261
- \$D REBLD command
  - display rebuild job queue 45
- \$O command
  - how to change output disposition 126
- \$P command
  - closing procedure library 103
- \$P JES2 start option
  - specifying 29
- \$SCAN macro 32

## Numerics

- 1403 printer
  - print chain alias for 131
- 3211 indexing
  - JCL OUTPUT statement 132
- 3211 printer
  - indexing for 132
  - print chain alias for 131
- 3800-3
  - compatibility mode 134
  - compatibility-mode support 134
  - full-function mode 134
  - support 132
- 3800 printer
  - page-mode printer support 65

## A

- abnormal end
  - in functional subsystem 67
  - JES2 67
- abnormal output disposition
  - how to define 124
  - OUTDisp= parameter 124
- access list 348

- access to resources
  - defining JES2 to RACF 344
- accessing data sets 349
- accounting 265
- accounting field scan
  - description 84
- add new MAS (multi-access spool) member
  - new member 60
- address space
  - functional subsystem 65
- addressable unit of output
  - line 134
  - page 134
- advanced program-to-program communication 112
- AFP (advanced function printer)
  - support 132
  - use 134
- all-member warm start 41
- allocation IOT (input/output table)
  - defining 167
- alternate checkpoint data set 29
- alternate subsystem
  - example 53
  - start as primary 53
- AMASPZAP patching statement 15
- APPL(avvvvvvv) initialization statement 6
  - LOGMODE parameter 287
- application program
  - providing copy of checkpoint 252
- application-to-application sessions (SNA NJE)
  - APPLID= parameter 283
  - special considerations 283
  - system requirements 283
- attribute
  - defining 95
- authorizing
  - inbound work 353
  - NJE job 355
  - NJE SYSOUT 356
  - NJE work 353
  - outbound work 359
  - use of input sources with RACF 352
- AUTOEMEM option
  - Make job eligible to restart 245
  - reset the checkpoint lock 245
- automatic command
  - example of processing 384
  - limit considerations 385
  - processing 383
  - security consideration 372
- automatic logon
  - for SNA RJE 333
- automatic restart management
  - batch jobs 127
  - started tasks 127
  - SYSOUT disposition 127
- automatic terminal connection
  - initiating 333

## B

- batch job
  - controlling workload 99
  - groupid validation 350
  - operator control of workload 94
  - password validation 350
  - securing resources 350
  - userid validation 350
  - validating groupid 350
  - validating passwords 350
  - validating userids 350
- best JOE (job output element) 120
  - determining 117
- bind image
  - \$HASP190 message 337
  - FCBLOAD parameter 337
  - JES2 337
  - older devices 337
  - R(nnnn).PR(m) statement 337
  - use 337
- block character routine 409
- BSC (binary synchronous communication) 74, 270, 274
  - capability 306
  - CTC (channel-to-channel) connection 257
  - definition 257
  - example 274
  - factors affecting performance 259
  - LINE(nnnn) initialization statement 274
  - LINENUM= parameter 274
  - NJEDEF initialization statement 274
  - node definition on NODE(nnnn) initialization statement 310
  - NODENUM= parameter 274
  - OWNNODE= parameter 274
  - requirement for starting node 291
  - resistance 301
  - use of RTAM 257

## C

- cataloged procedure
  - creating 23
  - for functional subsystem 52, 54
  - specify user PROCLIBs 25
- central storage
  - as a performance factor 386
  - insufficient 386
- change log size
  - controlling 200
  - duplex checkpoint mode 200
- characteristic
  - determining 113
- characteristic of a job class 86
- checkpoint
  - reconfiguration 228
- checkpoint data integrity
  - VOLATILE= parameter 198
- checkpoint data set
  - \$HASP271 message 224

- checkpoint data set (*continued*)
  - \$HASP272 message 225
  - \$HASP282 message 225
  - allocate space 205, 206
  - avoiding disruption 216
  - calculating size 201
  - configuration 195
  - controlled access 221
  - coupling facility lock 56
  - coupling facility storage 206
  - creating multiple copies 253
  - cycle description 208
  - DASD lock 56
  - data set name 223
  - define NEWCKPTn replacement 223
  - definition 195
  - dialog 228
  - DSNAME=definition 223
  - error situation 216
  - forwarding defined 225
  - forwarding example 226
  - function 195
  - initiating 228
  - JES2 member failure on coupling facility 245
  - JES2 member failure on DASD 245
  - MAS (multi-access spool) configuration 56
  - MASDEF initialization statement 221
  - MVS and JES2 member failure 245
  - phase I- RESERVE, lock, and read 210
  - phase II - updating 211
  - phase III - final write and release 211
  - phase IV - other member access 211
  - placement 196, 225
  - placing on coupling facility 207
  - providing copies of 252
  - recommendation for 199
  - reconfiguration dialog 224, 228
  - recovery through reconfiguration 240
  - respecifying 224
  - restarting JES2 234, 244
  - restriction in using volumes for 199
  - space allocation 223
  - space management consideration 201
  - specifications 197
  - storage requirements 206
  - STRname= definition 223
  - structure storage requirements 206
  - syntax on JCL SPACE parameter 205
  - use during reconfiguration dialog 225
  - versioning 253
  - VOLser= definition 223
  - volume serial 223
  - when DUPLEX=OFF 216

- Checkpoint data set
  - controlling contention-driven access 223
- checkpoint on coupling facility
  - benefit 197
  - define 198
  - initialize 198
  - recommendation 198



- checkpoint reconfiguration dialog
  - follow-up 241
  - I/O error as cause 230, 234
  - JES2-initiated 233
  - operator-initiated 238
  - volatile coupling facility as cause 237
- checkpointing
  - definition 195
- checkpointing DUAL mode
  - processing 217
- checkpointing duplex mode
  - with backup 212
  - without backup 216
- checkpointing method of operation
  - MAS (multi-access spool) 221
  - phases 221
- CKPT1 start option 29
- CKPT2 start option 29
- CKPTDEF initialization statement
  - CKPT1= parameter 200
  - CKPT2= parameter 200
  - LOGSIZE= parameter 200
  - providing copy of checkpoint 252
- class assignment
  - SYSOUT (system output) 113
- Client Print Services
  - support 131
- COLD start option
  - specifying NOREQ 29
- command display
  - JES2 response 76
- command input
  - controlling commands 364
- command prefix 13
- COMPACT statement
  - building compaction table 268
  - data compaction 268
  - using compaction table 268
- compaction
  - description 330
  - how it works 330
- compatibility mode
  - for 3800-3 printer 134
  - for page-mode printer 134
- compatibility-mode support
  - for 3800-3 printer 134
- conchar parameter
  - CONDEF initialization statement 13
- CONCHAR parameter
  - to specify command and message prefix 13
- configuration
  - configuration 76
  - defining 76
  - internal reader 76
  - local device 73
  - multi-access spool 58
  - remote device 74
  - simple NJE network 274
  - spool 163
- configuration change
  - output routing 145
- CONNECT statement
  - prevent looping 297
- connecting the network 290
- connection
  - automatic 331
  - between functional subsystem components 66
  - determine resistance value 301
  - remote start/stop 332
- connection in a network
  - PATH= parameter 306
  - RESTMAX= parameter 306
  - RESTTOL= parameter 306
- connections
  - adding a node to a network 309
- console
  - area 76
- CONSOLE control statement
  - initialization 14
- CONSOLE start option
  - specifying \$P JES2 29
- CONSOLxx MVS statement 43
- Control non-local resistance
  - SENTREST= parameter 304
- control of queue
  - multi-access spool configuration 221
- control of system output
  - JCL OUTPUT statement 104
- control statement
  - /\*\$VS 101
  - /\*NETACCT 84
  - /\*PRIORITY 89
  - /\*SIGNON description 332
  - system command 101
- controlling access to data sets 349
- controlling commands
  - command input 364
  - using RACF 364
- controlling contention-driven access
  - DORMANCY= parameter 223
  - HOLD= parameter 223
- controlling initialization
  - CONSOLE statement 14
  - DISPLAY statement 14
  - LIST=NO statement 14
  - LIST statement 14
  - LOG control statement 14
  - LOG=NO statement 14
- controlling loading
  - LOADMOD(jxxxxxxx) initialization statement 34
- controlling output
  - external writer 364
  - nodes 363
  - printers 363
  - punches 363
  - workstations 363
  - writer, external 364
- controlling system output
  - functional subsystem support 104
- controlling who can issue commands
  - using RACF 364



- conversion
  - controlling 83
  - JCL (job control language) 83
  - parameter 83
- coupling facility attribute
  - correcting for 208
- coupling facility incorrect size
  - correcting for 207
- coupling facility resource management policy
  - define 11
- CTC (channel-to-channel) connections 257

## D

- DASD utilization
  - initialization statements recommendations 379
- data compaction
  - definition 268
- data compression
  - definition 268
- data process mode 135
- data set
  - controlling access to 349
  - JES2 checkpoint 199
  - JES2 checkpoint on coupling facility 198
  - JES2 spool 163
- data sets residing on spool
  - securing 359, 360
- DATASET profile
  - use 349
- DD JCL statement
  - affect on output disposition 126
  - HOLD= parameter 126
  - SEGMENT= parameter 128
- dedication
  - line 74
- default data set characteristic
  - JCL OUTPUT statement 115
- default name
  - NJE node 271
- default names
  - NODE(nnnn) statement 271
- default userid
  - concepts 356
  - translating 358
- defining an attribute 95
- defining JES2 to RACF 344
- defining NAME (member names)
  - MEMBER initialization statement 59
- defining node names
  - NAME= parameter 271
  - restriction 271
- defining private connection
  - PRIVATE= parameter 294
- DELAY= parameter
  - NJEDEF initialization statement 312
- deletion of spool volumes
  - dynamic 173
- demand setup 115
  - grouping characteristic 115
- demand setup and output data set grouping 115
- design consideration
  - network 264
- DEST= parameter
  - JCL DD statement 263
  - JCL OUTPUT statement 263
  - JES2 /\*OUTPUT statement 263
- DESTDEF initialization statement
  - alter destination processing 152
  - LOCALNUM= parameter 152
- DESTID(jxxxxxxx) initialization statement
  - default NJE configuration 274
  - destination identifier 273
  - example of a destination identifier 309
  - first-level destination 142
  - name 274
  - output routing 142
  - relation to NODE(nnnn) initialization statement
    - subscript 274
  - scope 274
  - second-level destination 142
  - subscript 274
- destid subscript
  - route jobs 81
- destination identifier
  - at the destination node 147
  - at the origin node 147
  - control 339
  - DEST= parameter 263, 273, 338
  - DESTID(jxxxxxxx) 309
  - destination resolution by JES2 147
  - determining output destination 263
  - first-level destination 143
  - messages 339
  - responses 339
  - route to RJE device 156
  - routing multiple destids 156
  - rules for JES2 processing 147
  - second-level destination 143
  - spooling 339
- destination node
  - determining output destination 263
- destination processing
  - alter through DESTDEF 152
  - preparing to alter 154
- determining destination
  - /\*Route control statement 263
  - JCL DD statement 263
  - JCL OUTPUT statement 263
  - JES2 /\*OUTPUT statement 263
- determining output destination
  - OUTADD macro 263
  - PRTDEST= parameter on R(nnnn).RD(m)
    - initialization statement 263
  - PRTDEST= parameter on RDR(nn) initialization
    - statement 263
  - PUNDEST= parameter on R(nnnn).RD(m)
    - initialization statement 263
  - PUNDEST= parameter on RDR(nn) initialization
    - statement 263
- device partitioning 171
- device utilization
  - and initialization statement specification 379
- devices supported by JES2 379

- disconnect line
  - automatic 331
  - remote line 331
- diskette writer
  - 3540 diskette 135
  - create output 135
- DISPLAY control statement 14
- displaying messages
  - in languages other than English 385
- disposition of output
  - \$O command 126
  - defining abnormal end disposition 124
  - defining normal end disposition 124
  - how to define default 124
  - how to override 126
  - OUTDisp= parameter 124
- DMNDSET= parameter
  - OUTDEF initialization statement 115
- DORMANCY parameter
  - minimum time receive requests ignored 312
  - recommendation for a member under VM 222
  - recommendation for heavy TSO (time-sharing options) 223
  - recommendation for member 222
  - recommendation for single processor 222
  - recommendation when printing 223
  - recommendation when running heavy batch 223
  - recommended value 221
- dynamic addition and deletion of spool volumes 171

## E

- emergency checkpoint
  - use when restarting JES2 242
- ENDNODE= parameter
  - prevent store-and-forward 305
- ESTBYTE initialization statement 100
- ESTLNCT initialization statement 100
- ESTPAGE initialization statement 100
- ESTPUN initialization statement 100
- event notification facility (ENF)
  - start and stop JES2 40
- execution
  - control 93
  - data sets needed for SYS1.HASPACE data set 163
  - data sets needed for SYS1.HASPKPT data set 199
- execution control statement
  - system action 88
- execution node
  - /\*ROUTE XEQ control statement 261
  - /\*XEQ control statement 261
  - /\*XMIT control statement 261
  - determining with XEQDEST on R(nnnn).RD(m) 261
  - determining with XEQDEST on RDR(nn) 261
- exit 1 use
  - output separation 137
- exit 11 use 174
- exit 12 use 174
- exit 14 usage 93
- exit 15 use
  - output separation 137

- exit 2 usage 91, 93
- exit 22 usage 91, 93
- exit 3 usage 84
- exit 49 usage 92, 93
- exit 6 usage 84, 91, 93
- exit 9 usage 100
- external writer 395
  - block characters to separate jobs 409
  - characteristics 395
  - description 157, 395
  - features of IBM-supplied version 395
  - overview 395
  - parameter list 400
    - format and content 400
  - selection criteria
    - data set 396
  - starting the external writer 396
  - using the 3800 Printing Subsystem 399
  - XWTR cataloged procedure 396
    - for the 3800 Printing Subsystem 399
    - modifying for special print chains 399

## F

- failure
  - functional subsystem 67
- FCB (forms control buffer)
  - for 3211 printer 132
- first-level destination
  - DESTID(jxxxxxxx) initialization statement 142
- FORMAT start option
  - specifying COLD 29
- FORMDEF
  - use in a network 280
- FSS (functional subsystem)
  - address space 65
  - cataloged procedure change 52, 54
  - component 66
  - modification 52, 54
  - poly-JES environment 66
  - recovery procedure 67
  - support 65
- FSS(accccccc) initialization statement
  - define page-mode printing 133
- full-function mode
  - for 3800-3 printer 134
  - for AFP printer 134
  - for page-mode printer 134
- Function
  - using
    - MVS REPLY command 29
- functional subsystem
  - advanced function printing printer support 132
  - controlling system output 104
  - reconnection 47
- functional subsystem application 65, 134
- functional subsystem printer
  - hot start consideration 47

## G

### general considerations for networking

- accounting 265
- node names 265
- performance 264
- resistance 265
- security 264
- topology 264

### groupids

- translating 358

### grouping characteristic

- demand setup 115

## H

### hardware consideration

- 3704 communication controllers 258
- 3705 communication controllers 258
- CTC (channel-to-channel) adapters 258
- NJE 258
- NJE (network job entry) 258
- SDLC (synchronous data link control) 259
- TCU= parameter 258

### HASIASM member

- sample initialization data set 5

### HASIBLD member

- sample initialization data set 5

### HASIPARM member

- sample initialization data set 5

### HASIPROC member

- sample initialization data set 5

### HASISMPA member

- sample initialization data set 5

### HASPLIST data set

- example 19

### HASPPARM=ddname start option

- specifying CONSOLE 29

### HDRBUF parameter

- control header/trailer 83
- NJEDEF initialization statement 83

### held data set

- in NJE environment 157

### HOLD= DD parameter

- affect on output disposition 126

### HOLD parameter

- minimum time send requests ignored 312
- recommendation for a member under VM 222
- recommendation for heavy TSO (time-sharing options) 223
- recommendation for member 222
- recommendation for single processor 222
- recommendation when printing 223
- recommendation when running heavy batch 223

### hot start 42

### hot start consideration

- exit facility 46
- functional subsystem 47
- functional subsystem printer 47

## I

### I/O interface

- spool offload facility 179

### IASXWR00 module 399

### IBM devices

- DASD 379
- local card punch 379
- local card reader 379
- local printer 379
- PSF (printer service facilities) printer 379
- remote workstation 379
- support by JES2 379

### identify JES2 command

- conchar parameter 13

### IEFSD094 output separator routine 406

### IEFSD095 output separator routine 409

### improving JES2 processing 159

### inbound work

- authorizing 353

### indexing

- 3211 printer 132

### INIT(nnnn) initialization statement

- initiator 95

### initiator

- WLM managed 97

### initialization

- controlling 14
- controlling with JES2 exits 32
- correct error 49
- description 3
- modifying 4
- NJE (network job entry) 270
- process overview 3
- specifying option 29
- spool offload facility 179

### initialization data set

- contents 12
- creating 12
- defining 26
- example 16
- for multi-access spool configuration 54, 56

### initialization statement

- affecting SNA RJE workstations 318
- defining data set containing 12
- defining nodes 272
- defining private connection 294
- device utilization 379
- ESTBYTE 100
- ESTLNCT 100
- ESTPAGE 100
- ESTPUN 100
- list 6
- modifying 48
- NAME on MEMBER 310
- network initialization 270
- OWNMEMB on MASDEF 310
- scanning 32
- security-related 372

### initiator

- INIT(nnnn) initialization statement 95
- JES2 93

- initiator (*continued*)
  - logical 93
  - name 95
- input nodes as local SYSOUT source
  - description 359
- input source
  - authorization with RACF 352
- input to your system
  - securing 349
- insufficient central storage 386
- internal reader
  - example
    - allocation, dynamic 78
    - dynamic allocation 78
    - submitting from a task 77
    - submitting from job 77
  - maximum number of simultaneous job streams 76
  - using 77
- isolation of storage 386

## J

- JCL DD statement
  - DEST= parameter 263
- JCL JOB statement
  - using in job scheduling 88
- JCL OUTPUT statement
  - 3211 indexing 132
  - control of system output 104
  - default data set characteristic 115
  - demand setup 115
  - DEST= parameter 263
  - output class assignment 113
  - output routing 142
  - system data set characteristic 116
- JES2
  - \$HASP190 message 337
  - \$SCAN macro 32
  - exit 11 use 174
  - exit 12 use 174
  - exit 14 use 93
  - exit 2 use 91, 93
  - exit 20 use 91, 93
  - exit 22 use 93
  - exit 3 use 84
  - exit 44 use 93
  - exit 49 use 92, 93
  - exit 6 use 84, 91, 93
  - exit 9 use 100
  - FCBLOAD parameter 337
  - improving processing 159
  - job log 139
  - older devices 337
  - output separation 137
  - path manager 292
  - PPT, JES2 requirements 35
  - program properties table, JES2 requirements 35
  - providing security 344
  - R(nnnn).PR(m) statement 337
  - restart 40
  - RJE bind image 336, 337
  - scanning facility 32
- JES2 (*continued*)
  - SMF record 13
  - using RACF to provide security 344
- JES2 /\*OUTPUT control statement
  - DEST parameter 263
- JES2 access to resources
  - defining 344
- JES2 applications for SNA NJE
  - console display 288
- JES2 command prefix
  - specify 13
- JES2 control statement
  - processing 81
- JES2 initialization statement
  - resources affected 372
- JES2 job statistics
  - example 141
- JES2 load module
  - control 32
- JES2 managed initiator
  - cataloged procedure 93
  - in controlling execution 93
- JES2 member shutdown
  - by command 38
- JES2 message prefix
  - specify 13
- JES2 module
  - location 33
- JES2 NJE procedure
  - example of updated 23
- JES2 print separator
  - description 135
- JES2 procedure
  - backup 25
  - content 23, 25
  - updating 23
- JES2 punch separator
  - description 141
- JES2 restart
  - all-member warm start 41
  - by command 42
  - cold 40
  - from an emergency checkpoint 242
  - hot start 42
  - job journal to ease restart 48
  - quick start 41
  - single-member warm start 41
  - using automatic restart management 48
- JES2 spin data set
  - in NJE 115
- JES2 start
  - cold start 36
- JES2 XCF group
  - name of member 10
- JESNEWS data set
  - creating 137
  - use in a network 280
- JESNEWS profile
  - protecting 361
- job
  - authorizing NJE 355

- job (*continued*)
    - network 80
    - output limit definition 129
  - job class
    - assignment 86
    - characteristic of job 86
    - characteristics 86
    - example of assigning 95
    - number 86
    - STC (started task) 86
    - TSU (time sharing user) 86
  - job disposition
    - spool offload facility 185
  - job entry subsystem
    - assigning job identifiers 262
    - primary 50
  - job header
    - control assignment of job identifier 263
    - controlling job identifiers 263
    - RANGE= parameter 263
    - TSO/E userid 260
  - job identification 82
  - job information
    - SMF record summary 111
  - job journaling
    - performance consideration 387
    - to ease restart 48
  - job log
    - JES2 139
  - job monitor
    - byte 100
    - card 100
    - line 100
    - page 100
  - job network
    - example 192
    - in a MAS 195
    - spool offload facility 192
  - job output element
    - best 120
  - job queue
    - maximum time receive requests ignored 311
    - rebuild 45
    - rebuild by JES2 45
  - job queue rebuilt
    - display with \$D REBLD command 45
  - job queuing
    - by priority 88
    - controlling 86
    - in multi-access spool configuration 62
    - of held job 86
    - queue entry 86
  - job receiver
    - network 82, 84
  - job scheduling
    - member affinity 90
    - scheduling environment 90
  - job scheduling priority 88
  - job selection
    - disabling job execution 91
    - duplicate job names 91
  - job selection (*continued*)
    - enabling job execution 91
    - exits 91
    - held jobs 91
    - job class limits 91
    - WLM 97
    - workload management 97
  - JOB statement
    - accounting field scan 84
    - NOTIFY user 260
  - job stream
    - definition 101
  - job submission
    - in multi-access spool configuration 62
    - job,SYSOOUT transmitter 261
    - through a network 261
  - job submission security 351
    - authorizing substitute users 351
  - job,SYSOOUT transmitter
    - job submission 261
  - job transmitter
    - network 82
  - JOBCLASS(v) initialization statement
    - how JES2 interprets OUTDisp= parameter 125
    - modification 88
    - OUTDisp= parameter 124
    - purge output disposition 126
    - value for OUTDisp= parameter 125
    - XBM= parameter 103
  - JOBDEF initialization statement
    - example of RANGE= 308
    - JCLERR= parameter 84
    - pre-conversion scan 84
    - RANGE= parameter 188, 262
    - RASSIGN= parameter 188, 262
  - jobid (job identifier)
    - identification of jobs 82
  - jobnames
    - controlling job names 351
    - controlling with RACF 351
- ## L
- LIM= parameter
    - output record for line-mode 116
  - limit
    - output for a started task 130
    - output for a TSO LOGON 130
    - output for batch job 129
    - output for transaction program 129, 130
  - line
    - configuration 74
    - determining rate 301
    - options for disconnecting 331
    - resistance 301
  - line definition
    - backup RJE workstation 326
    - dedicated 326
    - multiple RJE workstations 326
    - nondedicated 326
    - shared 326

- line-mode
  - vs page-mode printing 134
- line-mode printer
  - vs page-mode printer 65
- line-mode printing 134
- LINE(nnnn) initialization statement
  - example of PASSWORD= parameter 308
- line start
  - \$S LINE(n) command 290
- LINENUM parameter of NJEDEF statement
  - example 275
- LIST control statement 14
- LIST=NO control statement 14
- list start option
  - HASPLIST data set 19
- Lnnnn.JT(m) statement
  - specify NJE Job transmitter 276
- Lnnnn.ST(m) statement
  - specify NJE SYSOUT transmitter 276
- load module
  - controlling JES2 load modules 32
  - loading installation-defined 34
  - table list 32
- LOADmod(jxxxxxxx)
  - controlling loading 34
- LOADmod(jxxxxxxx) initialization statement
  - \$HASP003 message 34
  - placement of load modules 34
  - STORAGE= parameter 34
- LOADMOD(jxxxxxxx) initialization statement
  - STORAGE= parameter 34
- local device
  - configuration 73
  - specifying number of 73
- local SYSOUT source
  - description of nodes as 359
- LOCALNUM= parameter
  - DESTDEF initialization statement 152
- location
  - SYS1.HASPACE data set 164
- lock
  - checkpoint 56
- LOG control statement
  - initialization 14
  - specifying 29
- LOG=NO control statement
  - initialization 14
- logical pooling
  - JES2 support 338
- LOGMODE parameter
  - APPL(avvvvvvv) initialization statement 287
  - NODE(nnnn) initialization statement 287
- logoff
  - type for SNA RJE workstation 335
- LOGOFF command
  - description 335
- logon
  - automatic 333
  - NOTIFY user 260
- LOGON command
  - description 334

## M

- MAILMSG= parameter
  - notify TSO/E userid 260
- MAS (multi-access spool) configuration
  - and JES2 XCF group 9
  - BSC node definition 310
  - checkpoint data set 56
  - define initialization data set 12
  - DELAY= parameter 312
  - ensure channel path 56
  - example 310
  - general description 54
  - job queuing 62
  - job submission 62
  - new member 41
  - NJE (network job entry) 309
  - node definition for SNA NJE 312
  - output 64
  - queue control 221
  - recommendation for specifying parameters for 56
  - recommendation for specifying statements for 56
  - RJE (remote job entry) 64
  - spool volume 56
  - start 58
  - TSO/E 64
  - warm start 41
- MASDEF initialization statement
  - delete member 61
  - DORMANCY= parameter 221
  - HOLD= parameter 221
  - message for 311
  - OWNMEMB= parameter 60, 310
  - queueing parameters 311
  - reassign identifier 61
  - recommended parameter values 221
  - redefine member 60
- member affinity
  - job scheduling 90
  - processor in independent mode 63
- MEMBER initialization statement
  - define new member 41, 59
  - NAME= parameter 60, 310
- message class 114
- message prefix 13
- message spooling
  - remote 340
- messages
  - displaying 385
- migration
  - spool offload facility 178
- minimum configuration statements
  - LINE(nnnn) initialization statement 274
  - LINENUM= parameter 274
  - NJEDEF initialization statement 274
  - NODENUM= parameter 274
  - OWNNODE= parameter 274
- mode of processing
  - example 117
- multi access spool (MAS)
  - security 375



- multileaving
  - RJE workstations supported by JES2 323
  - specifying buffer size 74
- MVS console
  - area 76
- MVS message service 385

## N

- NAME (member names)
  - MEMBER initialization statement 59
- naming restrictions
  - OWNNODE= parameter 271
  - sign-on verification 271
  - symbolic name 271
- NCP (network control program) 259
- SNA (system network architecture) 257
- network
  - backbone configuration 267
  - BSC overview 290
  - capability 275, 306
  - compatibility 257
  - connecting the network 290
  - connection overview 290
  - control jobs looping 278
  - defining private connection 294
  - definition 257
  - design considerations 264
  - displaying information about a network 287
  - general considerations 264
  - job flow through a network 259
  - maximum nodes 257
  - naming nodes 271
  - NODE(nnnn) initialization statement 270
  - parallel lines 309
  - PATHMGR= parameter 292
  - PRIVATE= parameter 294
  - processing of output groups (job output elements) 104, 107
  - public connection 296
  - security 269
  - simple SNA configuration 258
  - specifying characteristics 264
  - specifying non-JES2 node 292
  - specifying time tolerance 279
  - starting a session 279
  - use of MAXHOP= parameter 278
  - using different operating systems 279
- network accounting
  - control statement 84
- network configuration
  - BSC 258
  - SNA 258
- network connection control (NCC) records
  - path manager 292
- network job 80
  - receiver 82
- network job header
  - control 83
- network job receiver
  - controlling a job 83
  - controlling job transmitter 83
- network job trailer
  - control 83
- network job transmitter 82
  - controlling a job 83
- network performance
  - compaction 268
  - compression 268
  - factors affecting 268
- network topology
  - 2-node with 2 parallel links 265
  - 4-node ring 265
  - 4-node ring with full connectivity 266
  - 5-node star 266
  - complex configurations 266
  - definition 265
  - simple 2-node 265
  - simple configurations 265
- networking
  - RACF profiles 354
- NJE (network job entry) 274
  - affect of output disposition 127
  - authorizing job 355
  - authorizing SYSOUT 356
  - basic procedure 23
  - connecting the network 290
  - console display 288
  - control assignment of job identifier 263
  - default node name 271
  - default parameters 275
  - displaying information about a network 287
  - functions 270
  - general considerations 264
  - global parameter 288
  - hardware considerations for NJE 258
  - held data set 157
  - held output 280
  - initialization 270
  - JESNEWS data set 137
  - multi-access spool configuration 309
  - multiple password 273
  - network header 280
  - overview 257
  - path selection 305
  - processing 75
  - security 353
  - SMF record summary 291
  - special considerations 283
  - specifying characteristics 264
  - static connection 295
  - subnet 299
  - SYSOUT transmission 261
  - TSO/E OUTPUT command 280
  - TSO/E userid jobs 260
  - use of LINECT= parameter 280
  - userid 280
  - validating SYSOUT 356
  - VTAM log mode entry 287
- NJEDEF connection
  - adding a node to a network 309
- NJEDEF initialization statement
  - specifying transmitter, receiver 276



- NJEDEF initialization statement (*continued*)
  - TIMEtol= parameter 279
- node
  - as local SYSOUT source, description of 359
  - defining names 312
  - destination 263
  - multi-access spool members 309
  - naming restrictions 312
  - resistance tolerance 301
  - tolerance 301
- node attributes
  - console display 288
- node definition
  - initialization statement 272
- node destination
  - determining output destination 263
- node execution
  - determining 261
  - JES2 control statement 261
- node name 265
  - default name 271
  - defining 272
  - during initialization 272
  - example 272
  - generics 272
  - interpretation 272
- NODE(nnnn) initialization statement 310
  - default name 271
  - defining private connection 294
  - example of AUTH= parameter 308
  - example of NAME= parameter 307
  - example of PASSWORD= parameter 307
  - LOGMODE parameter 287
  - NAME= parameter 271
  - naming restrictions 271
  - PRIVATE= parameter 294
  - SUBnet= parameter 299
- NODENUM parameter of NJEDEF statement
  - example 275
- nodes as local SYSOUT source
  - description 359
- NOLIST start option
  - specifying NOLOG 29
- NOLOG start option
  - specifying CKPT1 29
- non-JES output writing routine 395
- NONE start option
  - specifying 29
- NOREQ start option
  - specifying NOLIST 29

## O

- offload process 362
- offloading spool
  - \$P OFFLOAD command 184
  - \$S OFFLOAD command 184
  - \$T OFFLOAD command 184
  - output disposition 127
  - value of OUTDisp= parameter 127

- operator command
  - addition of spool volumes 171
  - deletion of spool volumes 171
  - entering in job stream 101
  - in controlling initial status of device 16
  - job control in a network 260
  - message flow 260
  - number 16
  - stop and restart JES2 40
- outbound work
  - authorizing 359
- OUTCLASS(v) initialization statement 125
  - how JES2 interprets OUTDisp= parameter 125
  - OUTDisp= parameter 124
  - specifying truncation of blanks 114
  - value for OUTDisp= parameter 125
- OUTCLASS(V) initialization statement
  - value for OUTDisp= parameter 125
- OUTDEF initialization statement
  - demand setup 115
  - SEGLIM= parameter 128
  - start output group 108
- OUTDisp= parameter
  - allowable value 125
  - example 124
  - HOLD= parameter 126
  - OUTDisp= parameter 126
  - relationship with DD JCL statement 126
  - relationship with OUTPUT JCL statement 126
  - specify output disposition 124
- OUTPRTY initialization statement
  - PAGE= parameter 105
  - RECORD= parameter 105
- output
  - controlling system 103
  - criteria for group 108
  - define a limit for batch job 129
  - define a limit for transaction program 129
  - demand setup 115
  - DEST= parameter 263
  - destination 142
  - determining destination 263
  - divide into smaller units 128
  - held data set 157
  - how to define limit for a started task 130
  - how to define limit for a TSO logon 130
  - multi-access spool configuration 64
  - print separator format 135
  - printer/punch operation for 142
  - priority 104
  - queuing 111
  - routing 142
  - selection 106
  - setup characteristic of 114
  - setup defaults used 115
  - transmission to another node 127
  - using print/punch processor 107
- output class
  - assignment 113
  - consideration 113
  - PRMODE parameter 114

- output class (*continued*)
  - processing mode 114
- output class assignment
  - JCL OUTPUT statement 113
- output data set grouping 115
- output destination node
  - \$T O operator command 263
  - OUTADD macro 263
- output disposition
  - affect of \$O command 126
  - how to override 125, 126
  - how to specify the default 124
  - override order 126
  - overview 124
- output disposition change
  - MOD= parameter 127
  - OFF(n).SR 127
  - OFF(n).ST 127
- output group (job output element)
  - best on output queue 120
  - description 104
  - determining best on output queue 117
  - example 117
  - processing through network 107
  - spin 115
- OUTPUT JCL statement
  - 3211 indexing 132
  - controlling system output 104
  - default data set characteristic 115
  - demand setup 115
  - how to override output disposition 126
  - OUTDisp= parameter 126
  - output class assignment 113
  - output routing 142
  - system data set characteristic 116
- output record
  - LIM= parameter 116
  - PLIM= parameter 116
- output routing
  - capabilities 142
  - configuration change 145
  - DESTID(jxxxxxx) initialization statement 142
  - JCL OUTPUT statement 142
  - network 111
  - PRT(nnnn) initialization statement 143
  - PRT(nnnn) statement 142
  - PUN(nnnn) initialization statement 143
  - R(nnnn).PR(M) initialization statement 143
  - R(nnnn).PU(m) initialization statement 143
  - through destination identifiers 143
- output separation
  - modifying 137
- output separator routine
  - writing 408
- output separator routine for an external writer
  - block character routine by IBM 409
  - functions 409
  - invoking 409
  - module name IEFSD095 409
  - parameter list 411
  - description 406
- output separator routine for an external writer (*continued*)
  - IBM-supplied output separator routine 406
  - note on protection key 409
  - output from the routine 408
  - parameter list 407
  - requirements for writing 408
  - return codes 409
- OUTPUT TSO/E command
  - effect on output disposition 126
- output writing routine 400
  - coding conventions 403
  - description 399, 403
  - IBM-supplied routine 399
  - programming considerations 404
- OWNMEMB= parameter
  - MASDEF initialization statement 59
  - start new MAS member 59
- OWNNODE parameter of NJEDEF statement
  - changing default 278
  - example 275

## P

- page-mode printer
  - AFP (advanced function printer) 134
  - attributes 134
  - font sizes 134
  - support 65
  - vs line-mode printer 65
- page-mode printing 134
  - vs line-mode printing 134
- PAGEDEF
  - use in a network 280
- parallel lines
  - adjacent node 309
- parameter recommendation for a member under VM
  - DORMANCY= parameter 222
  - HOLD= parameter 222
- parameter recommendation for heavy TSO (time-sharing options)
  - DORMANCY= parameter 223
  - HOLD= parameter 223
- parameter recommendation for member
  - DORMANCY= parameter 222
  - HOLD= parameter 222
  - MASDEF initialization statement 222
- parameter recommendation for single processor
  - DORMANCY initialization parameter 222
  - HOLD initialization parameter 222
- parameter recommendation when printing
  - DORMANCY= parameter 223
  - HOLD= parameter 223
- parameter recommendation when running heavy batch
  - DORMANCY= parameter 223
  - HOLD= parameter 223
- partitioning of devices 171
- password
  - encrypting 269
  - multiple for (NJE) network job entry 273
  - PENCRYPT= parameter 269

- patch
  - description 15
  - statement
    - description 15
    - format 16
- patch statement
  - description 15
- PATH= parameter 306
- path manager 301
  - console display 289
  - description 292
  - network connection control (NCC) records 292
  - protocol within a network 293
  - specifying node without 292
- path resistance
  - alternate 305
  - determining 301
- path selection
  - alternate 305
  - determining path resistance 301
  - role of path manager 305
- PCE (processor control element)
  - running partially disabled 38
- PEP (partitioned emulation programming) extension
  - SNA (system network architecture) 257
- performance consideration
  - central storage 386
  - device partitioning 171
  - JES2 spool volume 174
  - job journaling 387
  - SMF exits 387
  - SMF records 387
  - spool 175
  - sufficient allocation of spool space 176
  - virtual storage 386
- performance considerations for JES2 Readers
  - held internal reader 80
  - use of RDINUM= parameter 80
  - use of unblocked records for SYSIN and SYSOUT data sets 80
- performance integrity
  - PROCLIB 25
- peripheral device support
  - under functional subsystem 65
- placement
  - SYS1.HASPACE data set 164
- placement of a load module
  - \$HASP003 message 35
  - LOADMOD(jxxxxxx) initialization statement 34
  - module placement 35
  - restriction 35
- PLIM= parameter
  - output record for page-mode 116
- poly-JES
  - functional subsystem consideration 66
- Poly-JES 50
- pooling remotes
  - JES2 support 338
  - RJE device 156
- PPT, JES2 requirements 35
- pre-cataloged data set
  - spool offload facility 181
- pre-conversion JCL scan
  - DD \* statement 84
  - DD DATA statement 84
  - JCLERR= parameter 84
  - JOB statement 84
  - JOBDEF initialization statement 84
- pre-execution offload
  - spool offload facility 182
- pre-execution reload
  - spool offload facility 186
- prefix
  - for JES2 commands 13
  - for JES2 messages 13
- print
  - output limit 129
- print chain
  - alias for 1403 and 3211 printers 131
- print separator format
  - example 135
- Print Services Facility
  - page-mode printer support 134
- print train
  - alias for 1403 and 3211 printers 131
- PRINTDEF initialization statement
  - size of separator page 135
- printer
  - considerations 131
  - process mode 135
- priority
  - associated with job output class 104
  - associated with processing interval 88
  - calculating 89
  - job scheduling 88
  - OUTPRTY initialization statement 105
  - PAGE= parameter on OUTPRTY statement 105
  - RECORD= parameter on OUTPRTY statement 105
- priority aging
  - limit 96, 106
- PRMODE= parameter
  - LINE= subparameter 135
  - PAGE= subparameter 135
- PRMODE parameter
  - output class assignment 114
- PRMODE specification
  - example 117
- procedure library
  - closing 103
  - selection 85
- process
  - offload 362
- process mode
  - LINE= subparameter 135
  - output class assignment 114
  - PAGE= subparameter 135
- processing
  - improving JES2 159
  - JES2 73
- processing JES2 control a statement 81

- processing mode specification
  - example 117
- PROCLIB
  - performance integrity 25
- profiles
  - NJE (network job entry) 354
- program properties requirements for JES2 35
- propagation
  - across a network 350
  - definition 350
  - of security information 358
- protecting
  - inbound work 353
  - JESNEWS 361
  - NJE job 355
  - NJE SYSOUT 356
  - NJE work 353
  - outbound work 359
  - SYSLOG data set 362
  - trace data sets 362
  - trace data sets, protecting 362
- providing copies of checkpoint data set
  - using VERSIONS on CKPTDEF 252
- providing copy of checkpoint
  - effect of NUMBER= 252
- PRT(nnnn) initialization statement
  - define page-mode printing 132
  - functional subsystem 132
  - output device 142, 143
  - output routing 142, 143
- PRTY keyword
  - JCL JOB statement 88
- public connection
  - network 296
- PUN(nnnn) initialization statement
  - output device 143
  - output routing 143
- punch
  - considerations 131
  - output limit 129
- purge output disposition
  - CONDPURG= parameter 126

## Q

- queue control in multi-access spool configuration 221
- queuing job
  - by priority 88
  - controlling 86
  - multi-access spool configuration 62
  - of held job 86
  - queue entry 86
  - queuing output 103
- quick start 41

## R

- R(nnnn).PR(m) initialization statement
  - output device 143
  - output routing 143
- R(nnnn).PU(m) initialization statement
  - output routing 143

- R(nnnn).PU(M) initialization statement
  - output device 143
  - output routing 143
- RACF (resource access control facility)
  - &RACLNDE profile 359
  - authorizing inbound work 353
  - authorizing outbound work 359
  - controlling who can enter commands 364
  - default userids 356
  - defining JES2 access to resources 344
  - defining users 347
  - groupid validation 350
  - grouping users 347
  - networking profiles 354
  - NJE jobs 355
  - NJE SYSOUT 356
  - nodes as local SYSOUT source 359
  - password validation 350
  - propagation 358
  - SECLABEL 348
  - security label description 348
  - SURROGAT class 351
  - translating default userids 358
  - translating security information 358
  - UACC (universal access authority) 348
  - userid validation 350
  - using for NJE 353
  - validating SYSOUT 356
- RANGE= parameter
  - JOBDEF initialization statement 263
- RDR(nn) initialization statement
  - example of PRNODE= parameter 309
- rebuild the job queue
  - with a JES2 restart 45
- rebuilt job queue
  - display with \$D REBLD command 45
- receiving data
  - from other nodes 264
- recommendation for an online system not requiring JES2 service
  - DORMANCY= parameter 223
  - HOLD= parameter 223
- RECONFIG start option
  - specifying HASPPARM=ddname 29
- reconfiguration dialog
  - reconfiguration 228
- reconnection
  - functional subsystem 47
- recovery for checkpoint reconfiguration
  - delayed member 241
  - driving member failure 240
  - JES2 member failure 240
  - start-up processing 241
- recovery procedure
  - functional subsystem 67
- recovery procedures
  - spool volume 174
- redirection
  - of display output 76
- reload security 362

- reloading spool
  - \$P OFFLOAD 186
  - \$S OFFLOAD 186
  - \$T OFFLOAD 186
  - output disposition 127
  - SAF userid verification during reload 187
  - value of OUTDisp= parameter 127
- remote message spooling 340
- remote output devices
  - example of 338
  - remote operator console 338
  - RJE workstation 338
- remote pooling
  - JES2 support 338
  - of device 142
- requeue jobs of failed member
  - using operator commands 246
  - using the AUTOEMEM option 248
- resistance 265
  - alternate path 305
  - determining path 301
  - specify maximum 305
- resources
  - defining JES2 access 344
- restart
  - automatic restart management 127
  - JES2 You can restart JES2 by either selecting 40
  - SYSOUT disposition 127
- restart JES2
  - after a system failure 48
  - after an orderly shutdown 38
  - from an emergency checkpoint 242
  - RECONFIG option 234, 244
  - with missing spool volume 46
- RESTMAX= parameter 306
- restrictions
  - /\*OUTPUT control statement 330
  - /\*OUTPUT JES2 control statement 330
  - multi-access spool nodes (SNA NJE) 312
- RESTTOL parameter 306
- RJE (remote job entry) 318
  - BSC buffer consideration 324
  - BSC considerations for 323
  - change line to BSC 329
  - change line to SNA 329
  - configuration of device 74
  - define BSC line 327
  - define line 325
  - define SNA line 329
  - description 317
  - dial-up connection 326
  - line password 329
  - modifying an RJE workstation 321
  - multi-access spool configuration 64
  - multileaving workstations supported 324
  - non-shared 327
  - PASSWORD= parameter 329
  - recovery from failed member 321
  - sharable 327
  - SMF record summary 325
  - SNA considerations for 322
  - RJE (remote job entry) 318 *(continued)*
    - starting 331
    - stopping 331
  - RJE (remote job entry) authorization
    - workstations 352
  - RJE bind image
    - JES2 336
    - use 337
  - RJE bind protocol 336
  - RJE device
    - pooling remotes 156
    - route to when Rdest=User 156
  - RJE initialization statement
    - RJE initialization 318
  - RJE workstation
    - altering the sequence of generations from 337
    - components of 74
    - control of 74
    - JES2 support 338
    - logical pooling 338
    - remote operator console example 338
    - remote pooling 338
    - specifying number of printers 74
    - specifying number of statement punches 74
    - specifying number of statement readers 74
  - RJE workstations
    - planning for growth 319
- RMT generation
  - description 324
  - specifying 324
- RMT(nnnn) initialization statement
  - specifying remote workstation 6
- RMTMSG= parameter
  - remote message spooling 340
  - TPDEF initialization statement 340
- route jobs
  - DEST parameter 81
- routing
  - output 142
- routing multiple destids
  - destination identifier 156

## S

- scanning
  - initialization statement 32
- scanning facility 32
- scheduling environment
  - job scheduling 90
- SDLC (synchronous data link control)
  - PEP (partitioned emulator program) 259
- second-level destination
  - DESTID(jxxxxxx) initialization statement 142
- secondary member
  - define 51
  - install 51
- securing resources
  - controlling job names 351
  - data sets JES2 uses 349
  - data sets residing on spool 359, 360
  - groupid validation 350

- securing resources *(continued)*
  - input to your system 349
  - nodes as local SYSOUT source 359
  - password validation 350
  - RJE workstations 352
  - SYSIN (system input) 359, 360
  - SYSLOG 362
  - SYSOUT (system output) 359, 360
  - userid validation 350
- security
  - cix1='exits, security-related'.security-related exit points 374
  - controlling job names 351
  - controlling who can issue commands 364
  - DATASET profile use 349
  - default userids 356
  - defining users to RACF 347
  - description 344
  - during offload 362
  - for inbound work 353
  - for outbound work 359
  - grouping users in RACF 347
  - job submission with RACF 351
  - label description 348
  - multi access spool (MAS) 375
  - network 269
  - NJE (network job entry) 353
  - NJE job 355
  - of NJE SYSOUT 356
  - overview 343
  - propagation 358
  - securing input source 352
  - securing resources overview 344
  - security-related 374
  - SMF record summary 347
  - spool offload facility 178, 362
  - SYSIN data sets 359, 360
  - SYSOUT data sets 359, 360
  - translating default userids 358
  - universal access authority 348
  - using RACF 344
- security label
  - description 348
  - RACSLUNK SECLABEL 349
  - translating 358
- security-related exit point 374
- security-related initialization statements 372
- seid=destin.destid 156
- SEGLIM parameter
  - segment output 128
- selecting SYSOUT based on
  - output disposition 127
- selective offload
  - spool offload facility 188
- selective reload
  - spool offload facility 190
- sending a display command
  - console display 290
- SENTREST= parameter
  - non-local resistance 304
- separator routine 406
  - parameter list 407
- separator routine 406 *(continued)*
  - parameter list 407
- service class
  - WLM classification 88
- set line density
  - \$HASP190 message 337
  - FCBLOAD parameter 337
  - older devices 337
  - PSERVIC 337
  - R(nnnn).PR(m) statement 337
  - remote printers 337
  - using bind image 337
- setup
  - change in characteristic 114
  - characteristic 114
- SIGNOFF statement
  - description of 332
- SIGNON statement 332
- single-member warm start 41
- SMF (System Management Facility)
  - performance consideration 387
- SMF record summary
  - job information 111
  - NJE (network job entry) 291
  - RJE (remote job entry) 325
  - security 347
  - spool offload facility 181
  - start JES2 39
  - stop JES2 39
- SMP/E (system modification program) 3
- SNA (system network architecture) 270
  - capability 282
  - configuring NJE sessions 281
  - defining NJE sessions 281
  - definition 257
  - determine output class 260
  - line configuration 74
  - minimum configuration 281
  - required initialization statement parameters 281
  - requirement for starting node 291
  - RJE workstation 322
  - RJE workstation starting 332
  - RJE workstation stopping 332
  - special considerations 283
  - specifying characteristics 264
  - supporting software 257
- specify NJE Job transmitter
  - Lnnnn.JT(m) statement 276
- specify NJE receiver
  - recommendation 277
- specify NJE SYSOUT transmitter
  - Lnnnn.ST(m) statement 276
- specify NJE transmitter
  - recommendation 277
- specifying a node without a path manager
  - PATHMGR= parameter 292
- specifying remote workstation
  - RMT(nnnn) initialization statement 6
- specifying transmitter, receiver
  - NJEDEF initialization statement 276



- spin data set
  - /\*OUTPUT control statement 115
  - DALCLOSE text unit key 115
  - end-of-task 115
  - freeing track 115
  - NJE (network job entry) 115
  - OUTPUT JCL statement 115
  - spool allocation 115
  - SVC99 dynamic allocation parameter list 115
  - when processed 115
- spool
  - allocation 176
  - configuration 163
  - data set 163
  - device allocation 166
  - device selection 175
  - fencing 168
  - maximum LRECL 166
  - partitioning 168
  - performance consideration 175
  - table 166
  - utilization limit 129
- spool allocation
  - spin data set 115
- spool configuration
  - multi-access queue control 221
- spool data set 163
  - securing contents 359, 360
- spool offload facility
  - I/O interface 179
  - initialization 179
  - job disposition 185
  - job network 192
  - migration 178
  - MOD= parameter 127
  - OUTDisp= parameter 127
  - output disposition 127
  - overview 178
  - pre-cataloged data set 181
  - pre-execution offload 182
  - pre-execution reload 186
  - protect offload data set 362
  - security 178
  - selective offload 188
  - selective reload 190
  - SMF record summary 181
  - uncataloged data set 180
  - work selection 180
- spool partitioning
  - through installation exit routine 174
- spool space
  - controlling 166
  - SPOOLDEF initialization statement 166
- spool volume
  - active status 172
  - add 172
  - division 163
  - drained status 172
  - draining status 172
  - dynamic addition 172
  - dynamic deletion 172
- spool volume *(continued)*
  - halting status 172
  - inactive status 172
  - MAS (multi-access spool) configuration 56
  - partition with FENCE= parameter 169
  - performance factor 174
  - recovery procedures 174
  - starting status 172
  - status 171
- SPOOLDEF initialization statement
  - defining the badtrack map 168
  - defining the master track group map 168
- spooling
  - remote messages 340
- SRM (system resource manager)
  - control of workload 99
- start and stop
  - JES2 35
- START command
  - example 38, 51
- start JES2
  - after a system failure 48
  - after an orderly shutdown 38
  - console display 36
  - for the first time 36
  - in a multi-access spool configuration 58
  - SMF record summary 39
  - START= member of IEFSSNxx parmlib. 36
  - START command in COMMNDxx parmlib. 36
- start new MAS member
  - OWNMEMB= parameter 59
- start option
  - specifying 27
  - specifying \$P JES2 29
  - specifying CKPT1 29
  - specifying COLD 29
  - specifying CONSOLE 29
  - specifying FORMAT 29
  - specifying HASPPARM=ddname 29
  - specifying NOLIST 29
  - specifying NONE 29
  - specifying NOREQ 29
  - specifying RECONFIG 29
- started task 78
  - control statements that affect the internal reader 79
  - discussion 78
  - example of conditional JCL submitted from a cataloged data set 79
  - example of console command to read job cataloged data set 78
  - example of console command to read job from tape 78
  - example of RDR procedure 78
  - example to submit from a tape through a batch job 78
  - output limit 130
- starting a session
  - NJEDEF TIMEtol= parameter 279
- starting line
  - \$S LINE(n) command 290



- starting node
  - BSC requirement 291
  - network path manager 291
  - SNA requirement 291
- static connection
  - alternate paths 297
  - console display 289
  - effect of multiple outage 298
  - example of CONNECT statement 296
  - operator command 297
  - prevent looping 298
  - private 295
  - use of CONNECT statement 295
- status
  - spool volume 172
  - spool volumes 171, 172
- stop JES2
  - SMF record summary 39
- storage
  - insufficient central 386
  - isolation 386
  - performance factor 386
- STORAGE= parameter
  - controlling loading 34
  - placement of a load module 34
- store-and-forward transmission
  - limit 305
  - REST= parameter 305
- submitter
  - validating 356
- subnet
  - defining, communicating between nodes 299
  - initialization stream example 299
  - with gateway node 266
- substitute user access
  - SURROGAT class 351
- subsystem
  - more than one JES2 50, 51
  - primary 51
  - restriction 51
  - secondary 50, 51
- subsystem support modules
  - addressing mode 34
  - loading 33
  - placement and storage consideration 34
  - referencing 34
- SUSPEND= parameter
  - for BSC RJE workstations 337
- suspend mode
  - for SNA RJE workstations 338
- symbolic destination identifier
  - console display 288
- synchronization tolerance 58
- SYS1.HASPACE data set
  - description 163
  - JES2 use 163
  - location 164
  - naming conventions 163
- SYS1.HASPCCKPT data set
  - as requirement for JES2 198, 199
  - contents of 199

- SYS1.HASPCCKPT data set (*continued*)
  - description 199
  - description of 199
  - description on coupling facility 198
- SYSLOG data set
  - protecting 362
- SYSOUT (system output)
  - authorizing NJE 356
  - NJE (network job entry) 157
  - specifying class for output 113
- SYSOUT (system output) class
  - for JESNEWS data set 138
- SYSOUT classes
  - use in a network 280
- SYSOUT Disposition
  - automatic restart management 127
- SYSOUT transmission
  - NJE 261
- System/360
  - Model 20 as RJE workstation 324
  - Model 22 as RJE workstation 324
- System/370 324
  - models as RJE workstation 324
- system data set characteristic
  - JCL OUTPUT statement 116
- system management facility
  - type 26 record 279

## T

- time-sharing task
  - logon 78
- tolerance
  - maximum time receive requests ignored 311
  - synchronization node 58
- trace data sets
  - protecting 362
- track
  - subdividing 170
- track cell
  - description 177
- track cell method
  - description 177
  - performance considerations 177
- track group maps
  - defining 168
  - TGSPACE=(MAX=) parameter 168
- transaction program
  - output limit definition 129
- translating
  - groupids 358
  - security labels 358
  - userid 358
- transmitter
  - network job 82
- transmitting held data set 127
- transmitting jobs for execution
  - store-and-forward 261
- truncation of blanks
  - OUTCLASS(v) initialization statement 114
- TSO/E (Time Sharing Option Extensions) 280

TSO/E (Time Sharing Option Extensions) 280  
     *(continued)*  
         job submission in a network 64  
         logon 64, 260  
         output limit 130  
         userid and JES2 151  
 TSO/E userid  
     MAILMSG= parameter 260  
     notify for mail 260  
 tuning  
     work selection criteria 121

## U

uncataloged data set  
     spool offload facility 180  
 update statement 23  
 userid  
     creating groups of 347  
     defining to RACF 347  
     security default 356  
     translating 358  
 USERSET= parameter  
     demand setup 115  
     OUTDEF initialization statement 115

## V

validating  
     groupid 350  
     passwords 350  
     security 356  
     userids 350  
 variable work selection criteria 116  
 versioning  
     for checkpoint data set copies 253  
 virtual storage  
     performance factor 386  
 VOLATILE parameter  
     checkpoint data integrity 198  
     ignore 199  
     specify a WTOR 199  
     specify DIALOG parameter 199  
 VTAM (Virtual Telecommunications Access Method)  
     define APPL statement for RJE 322  
     different logon mode for NJE session 287  
     SNA (system network architecture) 257  
     support for SNA RJE workstation 322  
 VTAM (Virtual Telecommunications Access Method)LU  
     definition  
         define LU statement for RJE 322  
 VTAM (Virtual Telecommunications Access Method)PU  
     definition  
         define PU statement for RJE 322

## W

warm start  
     authorization 43  
     considerations 43  
     for Automatic Restart Management restarted jobs 48

warm start *(continued)*  
     for journaled job 48  
     for non-journaled job 48  
     requeuing jobs for 48  
     specifying 29  
     writing a day's work scheduler 383  
     WTO buffer 43  
 warm start type  
     all-member warm start 41  
     hot start 42  
     quick start 41  
     single-member 41  
 work selection criteria 120  
     description 116  
     example 117, 120  
     offloading spool 127  
     reloading spool 127  
     specifying 117  
     spool offload facility 180  
     tuning 121  
     variable 116  
     WS= parameter description 116  
 workload management  
     classification 88  
     job selection 97  
 workstations  
     planning for growth 319  
 WTO buffer  
     CONSOLxx MVS statement 43  
     limit 43  
     wait 43

## X

XBM (execution batch monitoring facility)  
     conversion from previous release 102  
     initialization statement 103  
     overview 101  
     use 102  
 XCF (cross-system coupling facility)  
     determine JES2 XCF group name 9  
     example of JES2 member name 10  
     JES2 XCF group 9  
 XWTR cataloged procedure 396



---

# Readers' Comments — We'd Like to Hear from You

**z/OS**

**JES2 Initialization and Tuning Guide**

**Publication No. SA22-7532-00**

**Overall, how satisfied are you with the information in this book?**

|                      | Very Satisfied           | Satisfied                | Neutral                  | Dissatisfied             | Very Dissatisfied        |
|----------------------|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|
| Overall satisfaction | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |

**How satisfied are you that the information in this book is:**

|                          | Very Satisfied           | Satisfied                | Neutral                  | Dissatisfied             | Very Dissatisfied        |
|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|
| Accurate                 | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Complete                 | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Easy to find             | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Easy to understand       | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Well organized           | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Applicable to your tasks | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |

**Please tell us how we can improve this book:**

Thank you for your responses. May we contact you? ☐ Yes ☐ No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

---

Name

---

Address

---

Company or Organization

---

Phone No.



Cut or Fold  
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES

**BUSINESS REPLY MAIL**

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation  
Department 55JA, Mail Station P384  
2455 South Road  
Poughkeepsie, NY  
12601-5400



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold  
Along Line





Program Number: 5694-A01



Printed in the United States of America  
on recycled paper containing 10%  
recovered post-consumer fiber.

SA22-7532-00

