

ASA5510 配置手册

首先通过超级终端用串口线连接到 ASA5510 console 口上, 设置如图:



1. 设置主机名:

```
<config>#hostname szhdasa
```

2. 设置时区:

```
szhdasa<config>#clock timezone EST 7
```

3. 设置时钟:

```
Szhdasa#clock set 15:45:30 28 FEB 2008
```

4. 配置内接口 IP

```
Szhdasa<config>#int Ethernet 0/0
```

```
Szhdasa<config-if>#nameif inside
```

```
Szhdasa<config-if>#security-level 100
```

Szhndasa<config-if>#ip address 192.168.55.254 255.255.255.0

5 配置外部接口 IP

Szhndasa<config>#int Ethernet 0/1

Szhndasa<config-if>#nameif outside

Szhndasa<config-if>#security-level 0

Szhndasa<config-if>#ip address 210.X.X.X 255.255.255.248

6.配置用户名和密码

Szhndasa<config>#username admin password ***** encrypted

privilege 15 注：15 表示有最高权限

7.配置 HTTP 和 TELNET

Szhndasa<config>#aaa authentication telnet console LOCAL

Szhndasa<config>#http server enable

Szhndasa<config>#http 192.168.55.0 255.255.255.0 inside

Szhndasa<config>#telnet 192.168.55.0 255.255.255.0 inside

8.配置 site to site vpn

crypto map outside_map 20 match address outside_cryptomap_20_1

crypto map outside_map 20 set pfs

crypto map outside_map 20 set peer 210.75.1.X

crypto map outside_map 20 set transform-set ESP-3DES-SHA

crypto map outside_map 20 set nat-t-disable

crypto map outside_map interface outside

注：还可通过 http 方式用 ASDM 管理软件图形化配置 ASA

