

1/VIAIRIR

ASC X12 Release 4010

301 **Booking Confirmation (Ocean)**

Message Implementation Guide

Version 1.0.0



Change history

Version	Date	Comments
1.0.0	28-Jul-2017	Initial version

Contact our eCommerce team:

Hamburg Süd Customer Order Management

Willy-Brandt-Str. 59-61 20457 Hamburg Germany

Email: ecommerce@hamburgsud.com



Contents

1	Audience		5
2	General In	nformation	5
	2.1 Term	ninology	5
	2.2 Proc	essing Guidelines	6
	2.3 Fund	ctional Description	7
	2.4 Statu	us Indicators and Usage Indicators	8
	Status Ind	licators	8
	Usage Ind	licators	8
	Format		8
3	ANSI X12	301 segment table of contents	10
4	Branch Dia	agram	12
5	Segment I	Description	13
	Segment:	ISA Interchange Control Header	13
	Segment:	GS Functional Group Header	15
	Segment:	ST Transaction Set Header	17
	Segment:	B1 Beginning Segment for Booking or Pick-up/Delivery	18
	Segment:	Y3 Space Confirmation	19
	Segment:	Y4 Container Release	20
	Segment:	W09 Equipment and Temperature	21
	Segment:	N9 Reference Identification	22
	Segment:	N1 Name	24
	Segment:	N2 Additional Name Information	25
	Segment:	N3 Address Information	26
	Segment:	N4 Geographic Location	27
	Segment:	R4 Port or Terminal	28
	Segment:	DTM Date/Time Reference	29
	Segment:	EA Equipment Attributes	30
	Segment:	LX Assigned Number	32
	Segment:	L0 Line Item - Quantity and Weight	33
	Segment:	L5 Description, Marks and Numbers	35
	Segment:	H1 Hazardous Material	36
	Segment:	V1 Vessel Identification	37
	Segment:	SE Transaction Set Trailer	38
	Segment:	GE Functional Group Trailer	39
	Segment:	IEA Interchange Control Trailer	40





1 Audience

This document is intended for business, technical and EDI personnel engaged in establishing an electronic connection with Hamburg Süd for the purpose of receiving booking confirmations for bookings placed at Hamburg Süd via ASC X12 301 Release 4010.

The following chapters provide information regarding General Conventions and Message Specifications.

2 General Information

2.1 Terminology

Within this manual specific terminology will be used that you may not be familiar with. In order to give you some guidance, please find below the most important EDI terms and their according definitions.

Directory

An EDI directory is published three times a year and versioned. The version number is a four digit numeric code that is incremented by each release. The specifications within this manual conform to the directory approved by the ASC X12 Board in October 1997 the directory code of X12-4010.

Each directory contains sub-directories for messages, segments, composites and data elements, all of which may change with directory versions. However, since a directory version is permanent, there is no need to update computer applications when specific directory has been adopted.

Interchange

An interchange is a group of messages that are sent in one transmission. This means that it is possible to have more than one message within an interchange.

Message

A message can be described as a business transaction. Therefore, where appropriate, a message is often referred to as a transaction rather than a message. A transaction could be a new entry, a new line, a change to a line, a cancellation of line etc.

A full list of messages can be retrieved from a sub-directory within all directory versions, called the message directory. Each message has its own description and structure, which may differ by directory version.

Segment

A segment is uniquely identified by a three character mnemonic tag, which is used as a reference to a common group of business information. Usually this defines one segment contains one item of business data (i.e. field or attribute). For example Place of Origin, Port of Loading, Port of Discharge are all locations. The segment used for location is called R4. There are, however, segments that include more than one item of business data. For example Transport Mode, Voyage Number and Vessel are all classified as transport details included in the respective segment.

Whilst a message has a standard structure of segments, there is also a separate subdirectory for segments within directory versions, known as the segment directory. Each segment has its own description and structure, which may differ by directory version.



Service Segment

A service segment is a segment that contains non-business related data. These segments usually include interchanges and messages, in the form of headers and trailers. For example ISA and GS are typical service segments.

Segment Group

A segment group is a collection of segments that are related within a message structure. A simple example would be a group for details of transport. This would typically include a segment for the voyage (using Q2), reference (using N9) and the locations (using R4).

Composite Element

A composite element is a lower level of detail to identify business data within segment. It is normally used when a data item requires addition information. Each composite element has a unique code identifying it. A composite element could be used, for example when a data item is in the form of a code and it requires a type qualifier and also organization responsible for its maintenance.

Whilst a segment has a standard structure, there is also a separate subdirectory for composite elements within directory versions, known as the composite data element directory. Each composite element has its own description and structure, which may differ within directory version.

Data Element

A data element is the lowest level within the EDI structure for holding data. Each data element has a unique code identifying it. A data element can exist as a stand-alone element or as a sub-element within a composite element.

There is also a separate sub-directory for data elements within directory versions, known as the data element directory. Like many other sub-directories, the data element sub-directory contains descriptions and other information. In addition, some data elements also have associated code lists, which are published by organizations such as the International Standards Organization (ISO), or the United Nations. However, it is often possible for trading partners to use their own code list.

2.2 Processing Guidelines

Hamburg Süd is sending booking confirmations via 301 messages to the customer. A single message contains only one confirmation.

EDI communication depends on Trading Partnership and will be mutually defined within a separate agreement. Common protocols for the transmission of messages are e.g. FTP or SFTP.



2.3 Functional Description

Hazardous Material

Please note that all necessary information about Hazardous Material is being reported in the H1 segment. It's not possible to just flag the shipment as Hazardous and transfer the data in a reference or free text segment! Same also applies for the 300 Booking Request message!



2.4 Status Indicators and Usage Indicators

Status Indicators

Status Indicators ("M" and "C") form part of the ANSI X12 standard and indicate a minimum requirement to fulfill the needs of the message structure. They are not adequate for implementation purposes. The Status Indicators are:

<u>Value</u>	<u>Description</u>
M	Mandatory The entity marked as such must appear in all messages, and apply to these messages as well as to any associated implementation guidelines (and consequently is also a Usage Indicator).
С	Conditional The entity is used by agreement between trading partners

Usage Indicators

Usage Indicators are implementation—related indicators that further detail the use of "Conditional" Status Indicators. Usage Indicators are applied at all levels of the guidelines and shown adjacent to data items such as segment groups, segments, composite data elements and simple data elements. They dictate the agreed usage of the data items or entities.

The Usage Indicators are:

<u>Value</u>	Description
M	Mandatory Indicates the item is mandatory in the UN/EDIFACT message.
R	Required Indicates the item must be transmitted in this implementation.
D	Dependent Indicates that the use of the item is depending on a well-defined condition or set of conditions. These conditions must be clearly specified in the relevant implementation guideline.
0	Optional Indicates that this item is at the need or discretion of both trading partners.
Χ	Not Used Indicates that this item is not used in this implementation. If present, it will be disregarded.
NA	Not Recommended (Advised) Indicates the item needn't be transmitted in this implementation.
А	Advised Indicates the item must is recommended to be transmitted in this implementation.

Where an item within a segment group, segment or composite data element is marked with Usage Indicators "M" or "R", but the segment group, segment or composite data element has been marked "O" or "D" (or for that matter "X"), the item is only to be transmitted when the segment group, segment or composite of which it is a part, is used.

Format

The format is used to describe the official format requirements within ASC X12-4010 directory.

Examples

a3 3 alphabetic characters, fixed length



n6 6 numeric characters, fixed lengthan5 5 alphanumeric characters, fixed length

a..6 up to 6 alphabetic charactersan..35 up to 35 alphanumeric characters

n..6 up to 6 numeric characters



3 ANSI X12 301 segment table of contents

Functional Group ID=RO

Introduction:

This Draft Standard for Trial Use contains the format and establishes the data contents of the Confirmation (Ocean) Transaction Set (301) for use within the context of an Electronic Data Interchange (EDI) environment. The transaction set can be used to provide all the information necessary for an ocean carrier to confirm space, container, and equipment availability in response to the Reservation (Booking Request) (Ocean) Transaction Set (300); or to notify other parties such as terminal operators or other ocean carriers.

Heading:

М	Pos . <u>No.</u> 005	Seg. <u>ID</u> ISA	Name Interchange Control Header	Req. <u>Des.</u> M	Max.Use	Loop <u>Repeat</u>	Notes and Comments
M	008	GS	Functional Group Header	M	1		
М	010	ST	Transaction Set Header	М	1		
M	020	B1	Beginning Segment for Booking or Pick- up/Delivery	M	1		
Χ	025	G61	Contact	0	3		
Χ	030	Y6	Authentication	0	2		
М	040	Y3	Space Confirmation	М	1		
			LOOP ID - Y4			10	
	050	Y4	Container Release	0	1		
	051	W09	Equipment and Temperature	0	1		
	054	N9	Reference Identification	0	100		
Χ	055	R2A	Route Information with Preference	0	25		
			LOOP ID - N1			4	
	060	N1	Name	0	1		
	070	N2	Additional Name Information	0	1		
	080	N3	Address Information	Ο	2		
	090	N4	Geographic Location	0	1		
Χ	100	G61	Contact	0	3		
			LOOP ID - R4			20	
М	110	R4	Port or Terminal	М	1		
	120	DTM	Date/Time Reference	0	15		
Χ	130	W09	Equipment and Temperature	0	1		<u>.</u>
Χ	140	Н3	Special Handling Instructions	0	6		
	150	EA	Equipment Attributes	0	5		

Detail:

	Pos. <u>No.</u>	Seg. <u>ID</u>	<u>Name</u>	Req. <u>Des.</u>	Max.Use	Loop <u>Repeat</u>	Notes and Comments
			LOOP ID - LX			999	
M	010	LX	Assigned Number	М	1		




X	020	N7	Equipment Details	0	1		1
Χ	021	W09	Equipment and Temperature	0	1		
X	030	K1	Remarks	0	10		
	040	L0	Line Item - Quantity and Weight	0	1		
	050	L5	Description, Marks and Numbers	0	1		
X	055	L4	Measurement	0	1		
X	057	L1	Rate and Charges	0	1		
			LOOP ID - H1			10	
	060	H1	Hazardous Material	0	1		
Χ	070	H2	Additional Hazardous Material Description	0	10		
	080	V1	Vessel Identification	0	2		Ь
Χ	090	V9	Event Detail	0	10		

Summary:

	Pos. <u>No.</u>	Seg. <u>ID</u>	<u>Name</u>	Req. <u>Des.</u>	Max.Use	Loop <u>Repeat</u>	Notes and Comments
M	010	SE	Transaction Set Trailer	M	1		· ·
М	015	GE	Functional Group Trailer	M	1		
M	020	IEA	Interchange Control Trailer	M	1		



4 Branch Diagram





5 Segment Description

Segment: ISA Interchange Control Header

Position: 005

Loop:

Level: Heading Usage: Mandatory

Max Use:

Purpose: To start and identify an interchange of zero or more functional groups and

interchange-related control segments

Comments:

Notes: Example Syntax

ISA*00* *00* *ZZ*HAMSUD *ZZ*PARTNERID

*160526*2245*U*00401*053849086*0*P*>~

	Ref.	Data	<u></u>				
1.4	Des.	Element		Attributes			
M	ISA01	I 01	Authorization Information Qualifier	M ID 2/2			
			Code to identify the type of information in the Auth	orization Information			
			Provided values:	and the			
			00 No Authorization Information F Meaningful Information in I02)	resent (No			
М	ISA02	102	Authorization Information	M AN 10/10			
			Information used for additional identification or au	horization of the			
			interchange sender or the data in the interchange				
	10 4 00	100	information is set by the Authorization Information				
М	ISA03	103	Security Information Qualifier	M ID 2/2			
			Code to identify the type of information in the Sec	arity information			
			Provided values:	ot (No Mooningful			
			00 No Security Information Preser Information in I04)	it (No Meaninglui			
M	ISA04	104	Security Information	M AN 10/10			
			This is used for identifying the security information	about the			
			interchange sender or the data in the interchange				
М	ISA05	105	information is set by the Security Information Qua Interchange ID Qualifier	ifier (103) M ID 2/2			
141	10/100	103	Qualifier to designate the system/method of code				
			designate the sender or receiver ID element being				
			Provided values:				
			ZZ Mutually Defined				
M	ISA06	106	Interchange Sender ID	M AN 15/15			
			Identification code published by the sender for oth				
			the receiver ID to route data to them; the sender a value in the sender ID element	lways codes this			
			Provided values:				
М	ISA07	105	Interchange ID Qualifier	M ID 2/2			
			Qualifier to designate the system/method of code	structure used to			
			designate the sender or receiver ID element being qualified				
			Provided values:				
			ZZ Mutually Defined				
М	ISA08	107	Interchange Receiver ID	M AN 15/15			



			Identification code published by the receiver of the data; Wh it is used by the sender as their sending ID, thus other partie to them will use this as a receiving ID to route data to them	es sending
M	ISA09	108	Interchange Date M	DT 6/6
			Date of the interchange	
			Format YYMMDD	
			Example: 160526 (26th May 2016)	
M	ISA10	109	Interchange Time M	TM 4/4
			Time of the interchange	
			Format HHMM	
			5 L 0045 (40.45)	
M	ISA11	I10	Example: 2245 (10:45 pm) Interchange Control Standards Identifier M	ID 1/1
141	IOATT	110	Code to identify the agency responsible for the control stand	
			the message that is enclosed by the interchange header and	
			Provided values:	
			Refer to 004010 Data Element Dictionary for acceptable coo	le values.
M	ISA12	I11	Interchange Control Version Number M	ID 5/5
			This version number covers the interchange control segmen	ts
			Provided values:	
			00401 Draft Standards for Trial Use Approved for Publication by ASC X12 Procedures Rev through October 1997	
M	ISA13	l12	Interchange Control Number M	N0 9/9
			A control number assigned by the interchange sender	
M	ISA14	I13	Acknowledgment Requested M	ID 1/1
			Code sent by the sender to request an interchange acknowle (TA1)	edgment
			Provided values:	
М	ISA15	l14	0 No Acknowledgment Requested Usage Indicator M	ID 1/1
IVI	15A15	114		-
			Code to indicate whether data enclosed by this interchange test, production or information	envelope is
			Provided values:	
			P Production Data	
			T Test Data	
M	ISA16	I15	Component Element Separator M	AN 1/1
			Type is not applicable; the component element separator is and not a data element; this field provides the delimiter used separate component data elements within a composite data this value must be different than the data element separator segment terminator	I to structure;



Segment: **GS** Functional Group Header

Position: 008

Loop:

Level: Heading Usage: Mandatory

Max Use: 1

Purpose: To indicate the beginning of a functional group and to provide control information

Comments: 1 A functional group of related transaction sets, within the scope of X12

standards, consists of a collection of similar transaction sets enclosed by a

functional group header and a functional group trailer.

Notes: Example Syntax

GS*RO*HAMSUD*RECEIVER ID*20160526*2245*1000*X*004010~

			Data Element Summary		
	Ref.	Data			
М	<u>Des.</u> GS01	Element 479	Name Functional Identifier Code	Attr M	<u>ibutes</u> ID 2/2
IVI	3301	413	Code identifying a group of application related transaction		
			Provided values:	אכ ווע	#15
				1 20	12)
M	GS02	1.10	3		
M	G302	142	Application Sender's Code		AN 2/15
			Code identifying party sending transmission; codes agre partners	eu	o by trading
			Provided values:		
М	GS03	124	Application Receiver's Code	M	AN 2/15
			Code identifying party receiving transmission; codes agr	eed	to by
			trading partners		
			Trading Partner's ID		
М	GS04	373	Date	M	DT 8/8
			Date expressed as CCYYMMDD		
			Example: 20160526 (26th May 2016)		
М	GS05	337	Time	M	TM 4/8
			Time expressed in 24-hour clock time as follows: HHMM or HHMMSSD, or HHMMSSDD, where H = hours (00-23 (00-59), S = integer seconds (00-59) and DD = decimal decimal seconds are expressed as follows: D = tenths (0 hundredths (00-99) Example: 224529 (10:45:29 pm)	3), M secc	l = minutes onds;
М	GS06	28	Group Control Number	М	N0 1/9
			Assigned number originated and maintained by the send	der	
М	GS07	455	Responsible Agency Code	M	ID 1/2
			Code used in conjunction with Data Element 480 to iden	tify t	the issuer of
			the standard Provided values:		
			X Accredited Standards Committee X1	2	
М	GS08	480	Version / Release / Industry Identifier Code	M	AN 1/12
			Code indicating the version, release, subrelease, and in of the EDI standard being used, including the GS and G code in DE455 in GS segment is X, then in DE 480 posi version number; positions 4-6 are the release and subre the version; and positions 7-12 are the industry or trade identifiers (optionally assigned by user); if code in DE455	E se tions leas asso	egments; if s 1-3 are the e, level of ociation



segment is T, then other formats are allowed

Provided values:

Draft Standards Approved for Publication by ASC X12 Procedures Review Board through October 004010

1997



Segment: ST Transaction Set Header

Position: 010

Loop:

Level: Heading Usage: Mandatory

Max Use: 1

Purpose: To indicate the start of a transaction set and to assign a control number

Comments:

Notes: Example Syntax

ST*301*0001~

M	Ref. <u>Des.</u> ST01	Data Element 143	Name Transaction	n Set Identifier Code	<u>Attr</u> M	ibutes ID 3/3
			Code uniqu	ely identifying a Transaction Set		
			Provided va	llues:		
			301	Confirmation (Ocean)		
M	ST02	329	Transaction Set Control Number		M	AN 4/9
	Identifying control number that must be unique within the tra functional group assigned by the originator for a transaction					



Segment: **B1** Beginning Segment for Booking or Pick-up/Delivery

Position: 020

Loop:

Level: Heading Usage: Mandatory

Max Use: 1

Purpose: To transmit identifying numbers, dates, and other basic data relating to the

transaction set

Comments:

	Ref.	Data				
	Des.	<u>Element</u>	<u>Name</u>	<u>Attr</u>	<u>ibutes</u>	
	B101	140	Standard Carrier Alpha Code	0	ID 2/4	
			Standard Carrier Alpha Code			
M	B102	145	Shipment Identification Number	М	AN 1/30	
		Identification number assigned to the shipment by the shipper uniquely identifies the shipment from origin to ultimate destination; (Does not contain blanks or special characters)				
			Customer shipment identifier if exists. Else HSDG Booking Number.			
	B103	373	Date	0	DT 8/8	
	D100	0.00	Date expressed as CCYYMMDD	Ū	D1 0/0	
			Date of Booking Confirmation			
	B104	558	Reservation Action Code	0	ID 1/1	
			Code identifying action on reservation or offering			
			HSDG supports these values: A for accept, D for decline, U for update			
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.	



Segment: Y3 Space Confirmation

Position: 040

Loop:

Level: Heading Usage: Mandatory

Max Use: 1

Purpose: To specify confirmation information for space booking including numbers, dates,

and load time

Comments: 1 If space is available, all of the conditional data elements in segment Y3 are

required. If the requested space is not available, Y301 is the booking number

'decline'.

	Ref.	Data			
	Des.	Element			ibutes
М	Y301	13	Booking Number	M	AN 1/17
			Number assigned by the carrier for space reservation		
			HSDG Booking Number		
	Y302	140	Standard Carrier Alpha Code	0	ID 2/4
			Standard Carrier Alpha Code		
			Depending on the Brand: SUDU, ANRM or CCNR		
	Y303	373	Date	0	DT 8/8
			Date expressed as CCYYMMDD		
			ETD / sailing date at POL		
	Y304	373	Date	0	DT 8/8
			Date expressed as CCYYMMDD		
			ETA date at POD		
X	Y305	154	Standard Point Location Code	0	ID 6/9
X	Y306	112	Pier Name	0	AN 2/14
	Y307	373	Date	0	DT 8/8
			Date expressed as CCYYMMDD		
			Cut-off date		
X	Y308	337	Time	X	TM 4/8
	Y309	91	Transportation Method/Type Code	0	ID 1/2
			Code specifying the method or type of transportation for	the	shipment
			Always "O" ocean		
			Refer to 004010 Data Element Dictionary for acceptable	coc	le values.
	Y310	375	Tariff Service Code	0	ID 2/2
			Code specifying the types of services for rating purpose	s	
			used values:		
			PP for port to port		
			DD for door to door PD for port to door		
			DP for door to port		
			Refer to 004010 Data Element Dictionary for acceptable	coc	le values.
Χ	Y311	623	Time Code	0	ID 2/2
			Refer to 004010 Data Element Dictionary for acceptable	coc	le values.



Segment: Y4 Container Release

Position: 050

Loop: Y4 Optional

Level: Heading Usage: Optional

Max Use: 1

Purpose: To transmit information relative to containers available for release

Comments:

Notes: Y4 segments will be grouped by same Equipment Type (ISO Code)

	Ref.	Data			
	Des.	Element	<u>Name</u>	<u>Attr</u>	<u>ibutes</u>
	Y401	13	Booking Number	0	AN 1/17
			Number assigned by the carrier for space reservation		
			HSDG Booking Number		
X	Y402	13	Booking Number	0	AN 1/17
	Y403	373	Date	0	DT 8/8
			Date expressed as CCYYMMDD		
			local Cargo Pickup date		
X	Y404	154	Standard Point Location Code	0	ID 6/9
	Y405	95	Number of Containers	0	N0 1/4
			Number of shipping containers		
	Y406	24	Equipment Type	0	ID 4/4
			Code identifying equipment type		
			Equipment ISO Code		
X	Y407	140	Standard Carrier Alpha Code	0	ID 2/4
X	Y408	309	Location Qualifier	X	ID 1/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
X	Y409	310	Location Identifier	X	AN 1/30
Χ	Y410	56	Type of Service Code	0	ID 2/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.



Segment: W09 Equipment and Temperature

Position: 051

Loop: Y4 Optional

Level: Heading Usage: Optional

Max Use:

Purpose: To relate equipment type and required temperatures

Comments:

Notes: Reefer data used from first item ISO Code group.

	Ref.	Data	•		
	Des.	Element			ibutes
M	W0901	40	Equipment Description Code	M	ID 2/2
			Code identifying type of equipment used for shipment		
			Always "CZ"		
			Refer to 004010 Data Element Dictionary for acceptable		
	W0902	408	Temperature	X	R 1/4
			Temperature		
			Requested temperature		
	W0903	355	Unit or Basis for Measurement Code	X	ID 2/2
			Code specifying the units in which a value is being expre	esse	d, or
			manner in which a measurement has been taken		
			Always "CE"		
	14/0004	400	Refer to 004010 Data Element Dictionary for acceptable		
	W0904	408	Temperature	X	R 1/4
			Temperature		
			Requested temperature		
	W0905	355	Unit or Basis for Measurement Code	X	ID 2/2
			Code specifying the units in which a value is being expremanner in which a measurement has been taken	esse	d, or
			Always "CE"		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.
X	W0906	3	Free Form Message	0	AN 1/60
X	W0907	1122	Vent Setting Code	0	ID 1/1
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.
X	W0908	488	Percent	0	N0 1/3
	W0909	380	Quantity	0	R 1/15
			Numeric value of quantity		
			Ventilation setting (cbm).		
			Always "0" if ventilation is CLOSED.		



Segment: N9 Reference Identification

Position: 054

Loop:

Level: Heading Usage: Optional Max Use: 100

Purpose: To transmit identifying information as specified by the Reference Identification

Qualifier

Comments:

Notes: max. 3 occurences:

SI - Shipper

BN - Booking number FB - Fowarder reference

			Data Element Summary		
	Ref.	Data			
	Des.	Element			ibutes
M	N901	128	Reference Identification Qualifier	M	ID 2/3
			Code qualifying the Reference Identification		
			one of:		
			SI - Shipper		
			BN - Booking number FB - Fowarder reference		
			Refer to 004010 Data Element Dictionary for acceptable		le values
	N902	127	Reference Identification	X	AN 1/30
	14902	121			
			Reference information as defined for a particular Transa specified by the Reference Identification Qualifier	JCHOI	1 Set of as
Χ	N903	369	Free-form Description	Х	AN 1/45
X	N904	373	Date	0	DT 8/8
X	N905	337	Time	X	TM 4/8
X	N906	623	Time Code	0	ID 2/2
^	11000	020	Refer to 004010 Data Element Dictionary for acceptable	_	-
X	N907	C040	Reference Identifier	Ω	o valace.
^	11007	0010	To identify one or more reference numbers or identificat	•	numhers as
			specified by the Reference Qualifier		idilibera da
Χ	C04001	128	Reference Identification Qualifier	M	ID 2/3
			Code qualifying the Reference Identification		
			Refer to 004010 Data Element Dictionary for acceptable	e cod	le values.
Χ	C04002	127	Reference Identification	M	AN 1/30
			Reference information as defined for a particular Transa	actior	n Set or as
			specified by the Reference Identification Qualifier		
X	C04003	128	Reference Identification Qualifier	X	ID 2/3
			Code qualifying the Reference Identification		
			Refer to 004010 Data Element Dictionary for acceptable	e cod	le values.
X	C04004	127	Reference Identification	X	AN 1/30
			Reference information as defined for a particular Transa	actior	n Set or as
			specified by the Reference Identification Qualifier	.,	ID 0/0
X	C04005	128	Reference Identification Qualifier	X	ID 2/3
			Code qualifying the Reference Identification		
			Refer to 004010 Data Element Dictionary for acceptable		
X	C04006	127	Reference Identification	X	AN 1/30
			Reference information as defined for a particular Transa	actior	n Set or as



specified by the Reference Identification Qualifier



Segment: N1 Name

Position: 060

Loop: N1 Optional

Level: Heading Usage: Optional

Max Use: 1

Purpose: To identify a party by type of organization, name, and code

Comments: 1 This segment, used alone, provides the most efficient method of providing

organizational identification. To obtain this efficiency the "ID Code" (N104) must provide a key to the table maintained by the transaction processing

party.

2 N105 and N106 further define the type of entity in N101.

Notes: max. occurrence 2:

SH - shipper CN - consignee

	Ref.	Data	Data Element Gammary		
	Des.	Element	Name	Attr	ibutes
M	N101	98	Entity Identifier Code	M	ID 2/3
			Code identifying an organizational entity, a physical loca an individual	tion,	, property or
			values used: SH for shipper MC for trucker		
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
	N102	93	Name	X	AN 1/60
			Free-form name		
			Partner Name		
	N103	66	Identification Code Qualifier	X	ID 1/2
			Code designating the system/method of code structure undentification Code (67)	used	for
			Always 25 (Carrier's Customer Code)		
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
	N104	67	Identification Code	X	AN 2/80
			Code identifying a party or other code		
			HSDG partner code		
X	N105	706	Entity Relationship Code	0	ID 2/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
X	N106	98	Entity Identifier Code	0	ID 2/3
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.



Segment: N2 Additional Name Information

Position: 070

Loop: N1 Optional

Level: Heading Usage: Optional

Max Use:

Purpose: To specify additional names or those longer than 35 characters in length

Comments:

Ref. <u>Des.</u> N201		Name Name	Attributes M AN 1/60
		Free-form name	
		Partner Name 2	
N202	93	Name	O AN 1/60
		Free-form name	
		Partner Name 3	
	<u>Des.</u> N201	N201 93	Des. N201 Element 93 Name Name Free-form name Partner Name 2 Name N202 93 Name Free-form name Free-form name



Segment: N3 Address Information

Position: 080

Loop: N1 Optional

Level: Heading Usage: Optional

Max Use: 2

Purpose: To specify the location of the named party

Comments:

М	Ref. <u>Des.</u> N301	Data Element 166	Name Address Information	Attr M	ibutes AN 1/55
			Address information		
	N302	166	Address Information	0	AN 1/55
			Address information		



Segment: N4 Geographic Location

Position: 090

Loop: N1 Optional

Level: Heading Usage: Optional

Max Use: 1

Purpose: To specify the geographic place of the named party

Comments: 1 A combination of either N401 through N404, or N405 and N406 may be

adequate to specify a location.

2 N402 is required only if city name (N401) is in the U.S. or Canada.

	Ref. <u>Des.</u> N401	Data Element 19	Name City Name	Attr O	ibutes AN 2/30
	11401	19	Free-form text for city name	U	AN 2/30
	N402	156	State or Province Code	0	ID 2/2
			Code (Standard State/Province) as defined by appropria agency	ate g	overnment
	N403	116	Postal Code	0	ID 3/15
			Code defining international postal zone code excluding blanks (zip code for United States)	punc	tuation and
	N404	26	Country Code	0	ID 2/3
			Code identifying the country		
X	N405	309	Location Qualifier	X	ID 1/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
Χ	N406	310	Location Identifier	0	AN 1/30



Segment: R4 Port or Terminal

Position: 110

Loop: R4 Mandatory

Level: Heading Usage: Mandatory

Max Use:

Purpose: Contractual or operational port or point relevant to the movement of the cargo

Comments: 1 R4 is required for each port to be identified.

Notes: HSDG will report

POR as the origin of the transport

POL as the origin of the next transport leg POD as the destination of the next transport leg

PLD as the destination of the transport

М	Ref. <u>Des.</u> R401	Data <u>Element</u> 115	Name Port or Terminal Function Code	<u>Attr</u> M	ributes ID 1/1	
			Code defining function performed at the port or terminal a shipment	with	respect to	
			used values: R for Place of Receipt L for Port of Loading D for Port of Discharge			
			E for Place of Delivery		1	
	R402	309	Refer to 004010 Data Element Dictionary for acceptable Location Qualifier	X	ie values. ID 1/2	
			Code identifying type of location			
			For locations in the US: D Outside US: K			
			in case the D/K code is unknown: UN Refer to 004010 Data Element Dictionary for acceptable	000	lo valuos	
	R403	310	Location Identifier		AN 1/30	
	11400	010	Code which identifies a specific location	^	AIT 1700	
			Corresponding to Location Qualifier			
	R404	114	Port Name	0	AN 2/24	
			Free-form name for the place at which an offshore carrie terminates (by transshipment or otherwise) its actual occuproperty From L**04 (Place name)	r the place at which an offshore carrier origina sshipment or otherwise) its actual ocean carrie		
	R405	26	Country Code	0	ID 2/3	
			Code identifying the country			
			UN country code (2 characters)			
X	R406	174	Terminal Name	0	AN 2/30	
X	R407	113	Pier Number	0	AN 1/4	
	R408	156	State or Province Code	0	ID 2/2	
			Code (Standard State/Province) as defined by appropria agency L**05 State code	ite g	overnment	



Segment: DTM Date/Time Reference

Position: 120

Loop: R4 Mandatory

Level: Heading Usage: Optional Max Use: 15

Purpose: To specify pertinent dates and times

Comments: Notes:

Used for documentation cutoff, specified for POL only (R4=L)

	Ref.	Data			
	<u>Des.</u>	<u>Element</u>	<u>Name</u>	<u>Attr</u>	<u>ibutes</u>
М	DTM01	374	Date/Time Qualifier	M	ID 3/3
			Code specifying type of date or time, or both date and ti	me	
			Always 649		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.
	DTM02	373	Date	X	DT 8/8
			Date expressed as CCYYMMDD		
X	DTM03	337	Time	X	TM 4/8
X	DTM04	623	Time Code	0	ID 2/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.
X	DTM05	1250	Date Time Period Format Qualifier	X	ID 2/3
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.
X	DTM06	1251	Date Time Period	X	AN 1/35



Segment: **EA** Equipment Attributes

Position: 150

Loop:

Level: Heading Usage: Optional

Max Use: 5

Purpose: To specify attributes required for a piece of equipment

Comments: 1 When EA01 is "PCO", "PSE", "DHT", "DWI", "YEA" or "MCP", EA02 and

EA03 are required.

Notes: Only supplied if a Genset is required.

	Ref.	Data	·		
М	<u>Des.</u> EA01	Element 1402	Name Equipment Attribute Code	Attı M	ributes ID 2/3
			Code specifying attributes of a piece of equipment		
			Always "GEN"		
			Refer to 004010 Data Element Dictionary for acceptable	e coc	de values.
X	EA02	C001	Composite Unit of Measure	X	
			To identify a composite unit of measure (See Figures A examples of use)	Appe	ndix for
X	C00101	355	Unit or Basis for Measurement Code	M	ID 2/2
			Code specifying the units in which a value is being expr manner in which a measurement has been taken Refer to 004010 Data Element Dictionary for acceptable		
X	C00102	1018	Exponent	0	R 1/15
			Power to which a unit is raised		
X	C00103	649	Multiplier	0	R 1/10
			Value to be used as a multiplier to obtain a new value		
X	C00104	355	Unit or Basis for Measurement Code	0	ID 2/2
			Code specifying the units in which a value is being expression manner in which a measurement has been taken		
х	C00105	1018	Refer to 004010 Data Element Dictionary for acceptable Exponent	e coc O	ne values. R 1/15
^	C00105	1010	Power to which a unit is raised	U	K 1/15
X	C00106	649	Multiplier	0	R 1/10
Λ.	000100	0-10	Value to be used as a multiplier to obtain a new value	Ū	1. 1710
X	C00107	355	Unit or Basis for Measurement Code	0	ID 2/2
-			Code specifying the units in which a value is being expression manner in which a measurement has been taken Refer to 004010 Data Element Dictionary for acceptable		ed, or
X	C00108	1018	Exponent	0	R 1/15
			Power to which a unit is raised		
X	C00109	649	Multiplier	0	R 1/10
			Value to be used as a multiplier to obtain a new value		
X	C00110	355	Unit or Basis for Measurement Code	0	ID 2/2
			Code specifying the units in which a value is being expression manner in which a measurement has been taken		
х	C00111	1018	Refer to 004010 Data Element Dictionary for acceptable	e cod O	ne values. R 1/15
^	COUTT	1010	Exponent Power to which a unit is raised	U	K 1/13
			FOWER TO WITHOUT A WITH IS TAISED		



X	C00112	649	Multiplier	0	R 1/10
			Value to be used as a multiplier to obtain a new value		
X	C00113	355	Unit or Basis for Measurement Code	0	ID 2/2
			Code specifying the units in which a value is being expr manner in which a measurement has been taken	esse	ed, or
			Refer to 004010 Data Element Dictionary for acceptable	e coc	de values.
X	C00114	1018	Exponent	0	R 1/15
			Power to which a unit is raised		
X	C00115	649	Multiplier	0	R 1/10
			Value to be used as a multiplier to obtain a new value		
X	EA03	380	Quantity	X	R 1/15



Segment: LX Assigned Number

Position: 010

Loop: LX Mandatory

Level: Detail Usage: Mandatory

Max Use: 1

Purpose: To reference a line number in a transaction set

Comments:

M

Notes: HSDG reports one LX per container

Data Element Summary

Ref. Data

Des.ElementNameAttributesLX01554Assigned NumberM N0 1/6

Number assigned for differentiation within a transaction set

Item number (counter)



Segment: L0 Line Item - Quantity and Weight

Position: 040

Loop: LX Mandatory

Level: Detail
Usage: Optional
Max Use: 1

Purpose: To specify quantity, weight, volume, and type of service for a line item including

applicable "quantity/rate-as" data

Comments: 1 L013 is used to convey the total number of boxes, cartons, or pieces

contained on a pallet, skid, or slip sheet for the line item.

			Data Element Summary		
	Ref.	Data	Maria	A	9
	<u>Des.</u> L001	Element 213	Name Lading Line Item Number	Attr O	<u>ibutes</u> N0 1/3
			Sequential line number for a lading item		
			Item number (same as in LX)		
X	L002	220	Billed/Rated-as Quantity	Χ	R 1/11
X	L003	221	Billed/Rated-as Qualifier	X	ID 2/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	
	L004	81	Weight	X	R 1/10
			Numeric value of weight		
			Total gross weight (in kilogram)		
	L005	187	Weight Qualifier	Χ	ID 1/2
			Code defining the type of weight		
			always G (gross weight)		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.
	L006	183	Volume	X	R 1/8
			Value of volumetric measure		
			Measurement		
	L007	184	Volume Unit Qualifier	X	ID 1/1
			Code identifying the volume unit		
			Default X (cubic meter)		
			Refer to 004010 Data Element Dictionary for acceptable	cod	
	L008	80	Lading Quantity	X	N0 1/7
			Number of units (pieces) of the lading commodity		
			Always 1		
	L009	211	Packaging Form Code	X	ID 3/3
			Code for packaging form of the lading quantity		
			Always CNT		
.,		4=4	Refer to 004010 Data Element Dictionary for acceptable		
X	L010	458	Dunnage Description	0	AN 2/25
	L011	188	Weight Unit Code	0	ID 1/1
			Code specifying the weight unit		
			always K for kilogram		
	1.040	5 0	Refer to 004010 Data Element Dictionary for acceptable		
	L012	56	Type of Service Code	0	ID 2/2
			Code specifying extent of transportation service requested	ed	



			used values:		
			PP for port to port		
			DD for door to door		
			PD for port to door		
			DP for door to port		
			Refer to 004010 Data Element Dictionary for acceptable	coc	le values.
	1.040	000			
X	L013	380	Quantity	Χ	R 1/15
Χ	L014	211	Packaging Form Code	0	ID 3/3
			Refer to 004010 Data Element Dictionary for acceptable	coc	le values.
Y	I 015	1073	Refer to 004010 Data Element Dictionary for acceptable	COC Y	
X	L015	1073	Refer to 004010 Data Element Dictionary for acceptable Yes/No Condition or Response Code Refer to 004010 Data Element Dictionary for acceptable	X	ID 1/1



Segment: L5 Description, Marks and Numbers

Position: 050

Loop: LX Mandatory

Level: Detail
Usage: Optional
Max Use: 1

Purpose: To specify the line item in terms of description, quantity, packaging, and marks

and numbers

Comments: 1 L502 may be used to send quantity information as part of the product

description.

	Ref.	Data	·				
	Des.	Element 213	<u>Name</u>	<u>Attr</u>	<u>ributes</u>		
	L501		Lading Line Item Number	0	N0 1/3		
			Sequential line number for a lading item				
			Item number (same as in LX)				
	L502	79	Lading Description	0	AN 1/50		
			Description of an item as required for rating and billing purposes				
			Commodity				
X	L503	22	Commodity Code	X	AN 1/30		
X	L504	23	Commodity Code Qualifier	X	ID 1/1		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.		
X	L505	103	Packaging Code	0	AN 3/5		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.		
X	L506	87	Marks and Numbers	X	AN 1/48		
X	L507	88	Marks and Numbers Qualifier	0	ID 1/2		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.		
Χ	L508	23	Commodity Code Qualifier	X	ID 1/1		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.		
X	L509	22	Commodity Code	X	AN 1/30		
X	L510	595	Compartment ID Code	0	ID 1/1		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.		



H1 Hazardous Material Segment:

Position: 060

> Loop: H1 Optional

Level: Detail Usage: Optional

Max Use:

Purpose:

To specify information relative to hazardous material

1 This segment is required when the shipment contains hazardous material. Comments:

2 H107 is the lowest temperature for hazardous materials.

	Ref.	Data			
М	<u>Des.</u> H101	Element 62	Name Hazardous Material Code	Attr M	<u>ibutes</u> AN 4/10
IVI	пійі	02	Code relating to hazardous material code qualifier for re-	•••	
			hazardous materials	yula	ieu
			UN Number		
	H102	209	Hazardous Material Class Code	0	AN 1/4
			Code specifying the kind of hazard for a material		
			IMDG Class Code		
	H103	208	Hazardous Material Code Qualifier	0	ID 1/1
			Code which qualifies the Hazardous Material Class Code	e (20	09)
			Always I for IMO Code		
			Refer to 004010 Data Element Dictionary for acceptable	cod	le values.
	H104	64	Hazardous Material Description	0	AN 2/30
			Material name, special instructions, and phone number i	f an	y
			Description, cut to first 30 characters		
	H105	63	Hazardous Material Contact	0	AN 1/24
			Phone number and name of person or department to co	ntac	t in case of
			emergency 40 living 10 liv	- \	
	11400	000	Contact and phone (13 characters name, 10 digits phone		ANI 4/0
	H106	200	Hazardous Materials Page	0	AN 1/6
			The United Nations page number as required for the inte transport of hazardous materials	rnaı	lionai
			Page		
	H107	77	Flashpoint Temperature	Χ	N 1/3
			The flashpoint temperature for hazardous material		
			Flashpoint temperature in Celsius		
	H108	355	Unit or Basis for Measurement Code	Χ	ID 2/2
			Code specifying the units in which a value is being expre	esse	d, or
			manner in which a measurement has been taken		
			Always CE for Celsius		
			Refer to 004010 Data Element Dictionary for acceptable		
	H109	254	Packing Group Code	-	ID 1/3
			Code indicating degree of danger in terms of Roman nu	nbe	r I, II or III
			Package group		



Segment: V1 Vessel Identification

Position: 080

Loop:

Level: Detail
Usage: Optional

Max Use: 2

Purpose: To provide vessel details and voyage number

Purpose: Comments:

	Ref.	Data			
	Des.	<u>Element</u>	<u>Name</u>	<u>Attributes</u>	
	V101	597	Vessel Code	X	ID 1/8
			Code identifying vessel		
			Lloyd's / IMO		
	V102	182	Vessel Name	X	AN 2/28
			Name of ship as documented in "Lloyd's Register of Ship	os"	
	V103	26	Country Code	0	ID 2/3
			Code identifying the country		
	V104	55	Flight/Voyage Number	0	AN 2/10
			Identifying designator for the particular flight or voyage of	n wh	nich the
			cargo travels		
			Voyage Number (HSDG or partner number)		
X	V105	140	Standard Carrier Alpha Code	0	ID 2/4
X	V106	249	Vessel Requirement Code	0	ID 1/1
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
X	V107	854	Vessel Type Code	0	ID 2/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
	V108	897	Vessel Code Qualifier	0	ID 1/1
			Code specifying vessel code source		
			always L (Lloyd's / IMO)		
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.
X	V109	91	Transportation Method/Type Code	0	ID 1/2
			Refer to 004010 Data Element Dictionary for acceptable	cod	e values.



Segment: **SE** Transaction Set Trailer

Position: 010

Loop:

Level: Summary Usage: Mandatory

Max Use: 1

Purpose: To indicate the end of the transaction set and provide the count of the transmitted

segments (including the beginning (ST) and ending (SE) segments)

Comments: 1 SE is the last segment of each transaction set.

Notes: Example Syntax

SE*7*0001~

М	Ref. <u>Des.</u> SE01	Data Element 96	Name Number of Included Segments	Attr M	tributes N0 1/10		
M	SE02	329	Total number of segments included in a transaction set and SE segments Transaction Set Control Number	inclu M	ding ST AN 4/9		
			Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set				



Segment: **GE** Functional Group Trailer

Position: 015

Loop:

Level: Summary Usage: Mandatory

Max Use: 1

Purpose: To indicate the end of a functional group and to provide control informationComments: 1 The use of identical data interchange control numbers in the associated

functional group header and trailer is designed to maximize functional group integrity. The control number is the same as that used in the corresponding

header.

Notes: Example Syntax

GE*1*1000~

M	Ref. <u>Des.</u> GE01	Data Element 97	Name Number of Transaction Sets Included	<u>Attı</u> M	ributes N0 1/6
			Total number of transaction sets included in the function interchange (transmission) group terminated by the train this data element	_	
M	GE02	28	Group Control Number	M	N0 1/9
			Assigned number originated and maintained by the sen	der	



Segment: IEA Interchange Control Trailer

Position: 020

Loop:

Level: Summary Usage: Mandatory

Max Use: 1

Purpose: To define the end of an interchange of zero or more functional groups and

interchange-related control segments

Comments:

Notes: Example Syntax

IEA*1*053849086~

	Ret.	Data			
	Des.	Element	<u>Name</u>	Attr	<u>ributes</u>
M	IEA01	l16	Number of Included Functional Groups	M	N0 1/5
			A count of the number of functional groups included in a	an int	erchange
M	IEA02	I12	Interchange Control Number	M	N0 9/9
			A control number assigned by the interchange sender		