Db2 12 for z/OS

Application Programming Guide and Reference for Java

SC27-8846-02

Notes

Before using this information and the product it supports, be sure to read the general information under "Notices" at the end of this information.

Subsequent editions of this PDF will not be delivered in IBM Publications Center. Always download the latest edition from PDF format manuals for Db2 12 for z/OS (Db2 for z/OS in IBM Documentation).

2023-11-27 edition

This edition applies to Db2® 12 for z/OS® (product number 5650-DB2), Db2 12 for z/OS Value Unit Edition (product number 5770-AF3), and to any subsequent releases until otherwise indicated in new editions. Make sure you are using the correct edition for the level of the product.

Specific changes are indicated by a vertical bar to the left of a change. A vertical bar to the left of a figure caption indicates that the figure has changed. Editorial changes that have no technical significance are not noted.

© Copyright International Business Machines Corporation 1998, 2017.
US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this information..... xi
Who should read this information.....xi
Db2 Utilities Suite for z/OS.....xi
Terminology and citations.....xi
Accessibility features for Db2 12 for z/OS.....xii
How to send your comments about Db2 for z/OS documentation..... xii
How to read syntax diagrams.....xiii

Chapter 1. Java application development for IBM data servers..... 1

Chapter 2. Supported drivers for JDBC and SQLJ.....3
How to find the IBM Data Server Driver for JDBC and SQLJ version.....4
Db2 for z/OS and IBM Data Server Driver for JDBC and SQLJ versions..... 4
IBM Data Server Driver for JDBC and SQLJ versions and Db2 or Db2 Connect levels..... 6

Chapter 3. JDBC application programming..... 9
Example of a simple JDBC application.....9
How JDBC applications connect to a data source..... 11
Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ.....13
Connecting to a data source using the DataSource interface..... 20
How to determine which type of IBM Data Server Driver for JDBC and SQLJ connectivity to use....22
JDBC connection objects..... 23
Creating and deploying DataSource objects.....23
Java packages for JDBC support.....25
Learning about a data source using DatabaseMetaData methods.....25
DatabaseMetaData methods for identifying the type of data server.....26
Using DatabaseMetaData extensions to identify the Db2 Connect version and the IBM Data Server Driver for JDBC and SQLJ version..... 28
Variables in JDBC applications.....28
Comments in a JDBC application..... 29
JDBC interfaces for executing SQL.....30
Creating and modifying database objects using the Statement.executeUpdate method..... 30
Updating data in tables using the PreparedStatement.executeUpdate method..... 31
JDBC executeUpdate methods against a Db2 for z/OS server..... 33
Making batch updates in JDBC applications..... 33
Learning about parameters in a PreparedStatement using ParameterMetaData methods.....37
Data retrieval in JDBC applications..... 38
Calling stored procedures in JDBC applications..... 51
LOBs in JDBC applications with the IBM Data Server Driver for JDBC and SQLJ.....56
ROWIDs in JDBC with the IBM Data Server Driver for JDBC and SQLJ..... 61
Update and retrieval of timestamps with time zone information in JDBC applications..... 63
Distinct types in JDBC applications..... 70
Invocation of stored procedures with ARRAY parameters in JDBC applications.....70
Savepoints in JDBC applications..... 71
Retrieval of automatically generated keys in JDBC applications.....73
Named parameter markers in JDBC applications..... 76
Retrieving JSON documents from a ResultSet..... 79
Providing extended client information to the data source with IBM Data Server Driver for JDBC and SQLJ-only methods.....82

Providing extended client information to the data source with client info properties....83
Extended parameter information with the IBM Data Server Driver for JDBC and SQLJ....87
Using DB2PreparedStatement methods or constants to provide extended parameter information....88
Using DB2ResultSet methods or DB2PreparedStatement constants to provide extended parameter information....89
XML data in JDBC applications....90
XML column updates in JDBC applications....91
XML data retrieval in JDBC applications....93
Invocation of routines with XML parameters in Java applications....96
Binary XML format in Java applications....98
Java support for XML schema registration and removal....99
Bidirectional (BiDi) text layout transformation....101
Inserting data from file reference variables into tables in JDBC applications....103
Loading a Db2 for z/OS table by using an IBM Data Server Driver for JDBC and SQLJ method....105
Transaction control in JDBC applications....106
IBM Data Server Driver for JDBC and SQLJ isolation levels....106
Committing or rolling back JDBC transactions....107
Default JDBC autocommit modes....108
Exceptions and warnings under the IBM Data Server Driver for JDBC and SQLJ....108
Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ....111
Handling an SQLWarning under the IBM Data Server Driver for JDBC and SQLJ....113
Retrieving information from a BatchUpdateException....115
Memory use for IBM Data Server Driver for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS....116
Disconnecting from data sources in JDBC applications....117

Chapter 4. SQLJ application programming....119
Example of a simple SQLJ application....119
Connecting to a data source using SQLJ....121
SQLJ connection technique 1: JDBC DriverManager interface....121
SQLJ connection technique 2: JDBC DriverManager interface....122
SQLJ connection technique 3: JDBC DataSource interface....124
SQLJ connection technique 4: JDBC DataSource interface....125
SQLJ connection technique 5: Use a previously created connection context....126
SQLJ connection technique 6: Use the default connection....127
Java packages for SQLJ support....127
Variables in SQLJ applications....128
Indicator variables in SQLJ applications....129
Comments in an SQLJ application....132
SQL statement execution in SQLJ applications....132
Creating and modifying database objects in an SQLJ application....133
Performing positioned UPDATE and DELETE operations in an SQLJ application....133
Data retrieval in SQLJ applications....142
Calling stored procedures in SQLJ applications....152
LOBs in SQLJ applications with the IBM Data Server Driver for JDBC and SQLJ....153
SQLJ and JDBC in the same application....156
Controlling the execution of SQL statements in SQLJ....158
ROWIDs in SQLJ with the IBM Data Server Driver for JDBC and SQLJ....159
TIMESTAMP WITH TIME ZONE values in SQLJ applications....160
Distinct types in SQLJ applications....162
Savepoints in SQLJ applications....162
XML data in SQLJ applications....163
XML column updates in SQLJ applications....164
XML data retrieval in SQLJ applications....165
XMLCAST in SQLJ applications....167
Inserting data from file reference variables into tables in SQLJ applications....167

SQLJ utilization of SDK for Java Version 5 function....168
Transaction control in SQLJ applications....171
Setting the isolation level for an SQLJ transaction....171
Committing or rolling back SQLJ transactions....171
Handling SQL errors and warnings in SQLJ applications....172
Handling SQL errors in an SQLJ application....172
Handling SQL warnings in an SQLJ application....173
Closing the connection to a data source in an SQLJ application....173

Chapter 5. Java reactive applications for Db2 data servers....175

Chapter 6. Java stored procedures and user-defined functions....177
Setting up the environment for Java routines....177
Setting up the WLM application environment for Java routines....178
Runtime environment for Java routines....180
Moving from 31-bit Java routines to 64-bit Java routines....184
Defining Java routines and JAR files to Db2....186
Definition of a Java routine to Db2....186
Definition of a JAR file for a Java routine to Db2....190
Java routine programming....191
Differences between Java routines and stand-alone Java programs....191
Differences between Java routines and other routines....191
Static and non-final variables in a Java routine....192
Writing a Java stored procedure to return result sets....193
Techniques for testing a Java routine....194

Chapter 7. Preparing and running JDBC and SQLJ programs....197
Program preparation for JDBC programs....197
Program preparation for SQLJ programs....197
Binding SQLJ applications to access multiple database servers....198
Program preparation for Java routines....200
Preparation of Java routines with no SQLJ clauses....200
Preparation of Java routines with SQLJ clauses....202
Creating JAR files for Java routines....205
Running JDBC and SQLJ programs....206

Chapter 8. JDBC and SQLJ reference information....207
Data types that map to database data types in Java applications....207
Date, time, and timestamp values that can cause problems in JDBC and SQLJ applications....215
Data loss for timestamp data in JDBC and SQLJ applications....219
Retrieval of special values from DECFLOAT columns in Java applications....220
Use of PreparedStatement.setTimestamp to set values in TIMESTAMP WITH TIME ZONE columns....222
Properties for the IBM Data Server Driver for JDBC and SQLJ....223
Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products....224
Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 servers....253
Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS and IBM Informix....268
Common IBM Data Server Driver for JDBC and SQLJ properties for IBM Informix and Db2 on Linux, UNIX, and Windows systems....269
IBM Data Server Driver for JDBC and SQLJ properties for Db2 on Linux, UNIX, and Windows systems....270
IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS....274
IBM Data Server Driver for JDBC and SQLJ properties for IBM Informix....284
IBM Data Server Driver for JDBC and SQLJ configuration properties....288
Driver support for JDBC APIs....318

IBM Data Server Driver for JDBC and SQLJ support for SQL escape syntax ... 350
SQLJ statement reference information ... 350
SQLJ clause ... 350
SQLJ host-expression ... 351
SQLJ implements-clause ... 352
SQLJ with-clause ... 353
SQLJ connection-declaration-clause ... 355
SQLJ iterator-declaration-clause ... 356
SQLJ executable-clause ... 357
SQLJ context-clause ... 358
SQLJ statement-clause ... 359
SQLJ SET-TRANSACTION-clause ... 362
SQLJ assignment-clause ... 362
SQLJ iterator-conversion-clause ... 363
Interfaces and classes in the sqlj.runtime package ... 364
sqlj.runtime.ConnectionContext interface ... 365
sqlj.runtime.ForUpdate interface ... 369
sqlj.runtime.NamedIterator interface ... 369
sqlj.runtime.PositionedIterator interface ... 370
sqlj.runtime.ResultSetIterator interface ... 370
sqlj.runtime.Scrollable interface ... 373
sqlj.runtime.AsciiStream class ... 375
sqlj.runtime.BinaryStream class ... 376
sqlj.runtime.CharacterStream class ... 376
sqlj.runtime.ExecutionContext class ... 377
sqlj.runtime.SQLNullException class ... 385
sqlj.runtime.StreamWrapper class ... 385
sqlj.runtime.UnicodeStream class ... 387
IBM Data Server Driver for JDBC and SQLJ extensions to JDBC ... 388
DBBatchUpdateException interface ... 391
DB2BaseDataSource class ... 391
DB2Binder class ... 401
DB2BlobFileReference class ... 402
DB2CallableStatement interface ... 402
DB2ClientRerouteServerList class ... 409
DB2ClobFileReference class ... 410
DB2Connection interface ... 410
DB2ConnectionPool class ... 429
DB2ConnectionPoolDataSource class ... 433
DB2DatabaseMetaData interface ... 435
DB2Diagnosable interface ... 436
DB2DataSource class ... 437
DB2Driver class ... 438
DB2ExceptionFormatter class ... 439
DB2FileReference class ... 439
DB2JCCPlugin class ... 440
DB2JSONResultSet interface ... 441
DB2ParameterMetaData interface ... 442
DB2PooledConnection class ... 443
DB2PoolMonitor class ... 445
DB2PreparedStatement interface ... 448
DB2ResultSet interface ... 462
DB2ResultSetMetaData interface ... 466
DB2RowID interface ... 467
DB2SimpleDataSource class ... 468
DB2Sqlca class ... 468
DB2Statement interface ... 469
DB2SystemMonitor interface ... 472

DB2TraceManager class ... 475
DB2TraceManagerMXBean interface ... 478
DB2Types class ... 481
DB2Version class ... 482
DB2XADataSource class ... 483
DB2Xml interface ... 485
DB2XmlAsBlobFileReference class ... 487
DB2XmlAsClobFileReference class ... 488
DBTimestamp class ... 488
LoadResult class ... 490
JDBC differences between versions of the IBM Data Server Driver for JDBC and SQLJ ... 491
IBM Netezza connection through the IBM Data Server Driver for JDBC and SQLJ ... 499
Examples of ResultSetMetaData.getColumnName and ResultSetMetaData.getColumnLabel values ... 501
Error codes issued by the IBM Data Server Driver for JDBC and SQLJ ... 503
SQLSTATEs issued by the IBM Data Server Driver for JDBC and SQLJ ... 510
Commands for SQLJ program preparation ... 512
sqlj - SQLJ translator ... 512
db2sqljcustomize - SQLJ profile customizer ... 516
db2sqljbind - SQLJ profile binder ... 526
db2sqljprint - SQLJ profile printer ... 530

Chapter 9. Installing the IBM Data Server Driver for JDBC and SQLJ on Db2 for z/OS ... 533
Installing the IBM Data Server Driver for JDBC and SQLJ as part of a Db2 installation ... 533
Jobs for loading the IBM Data Server Driver for JDBC and SQLJ libraries ... 534
Environment variables for the IBM Data Server Driver for JDBC and SQLJ ... 534
Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties ... 536
Enabling the Db2-supplied stored procedures used by the IBM Data Server Driver for JDBC and SQLJ ... 537
DB2Binder utility ... 539
DB2LobTableCreator utility ... 547
Verify the installation of the IBM Data Server Driver for JDBC and SQLJ ... 548
Upgrading the IBM Data Server Driver for JDBC and SQLJ to a new version ... 550
Installing the z/OS Application Connectivity to Db2 for z/OS feature ... 551
Jobs for loading the z/OS Application Connectivity to Db2 for z/OS libraries ... 552
Environment variables for the z/OS Application Connectivity to Db2 for z/OS feature ... 553

Chapter 10. Setting the Db2 for z/OS application compatibility for your JDBC and SQLJ applications ... 555

Chapter 11. Installing, updating, or upgrading the IBM Data Server Driver for JDBC and SQLJ on Db2 on Linux, UNIX, and Windows systems ... 557
Special setup for accessing Db2 for z/OS servers from Java programs ... 560

Chapter 12. Security under the IBM Data Server Driver for JDBC and SQLJ ... 563
User ID and password security under the IBM Data Server Driver for JDBC and SQLJ ... 565
User ID-only security under the IBM Data Server Driver for JDBC and SQLJ ... 568
Encrypted password, user ID, or data security under the IBM Data Server Driver for JDBC and SQLJ ... 569
Kerberos security under the IBM Data Server Driver for JDBC and SQLJ ... 571
Requirements for Kerberos security under the IBM Data Server Driver for JDBC and SQLJ ... 575
IBM Data Server Driver for JDBC and SQLJ trusted context support ... 577
IBM Data Server Driver for JDBC and SQLJ support for SSL ... 579
Configuring connections under the IBM Data Server Driver for JDBC and SQLJ to use SSL ... 580
Configuring the IBM Data Server Driver for JDBC and SQLJ to use RACF key rings for SSL certificates ... 581
Configuring the Java Runtime Environment to use SSL ... 582

Certificate authentication under the IBM Data Server Driver for JDBC and SQLJ....585
Token authentication under the IBM Data Server Driver for JDBC and SQLJ....586
Security for preparing SQLJ applications with the IBM Data Server Driver for JDBC and SQLJ....587

Chapter 13. Java client support for high availability on IBM data servers....589
Java client support for high availability for connections to Db2 on Linux, UNIX, and Windows systems servers....590
Configuration of Db2 on Linux, UNIX, and Windows systems automatic client reroute support for Java clients....591
Example of enabling Db2 on Linux, UNIX, and Windows systems automatic client reroute support in Java applications....593
Configuration of Db2 on Linux, UNIX, and Windows systems workload balancing support for Java clients....594
Example of enabling Db2 on Linux, UNIX, and Windows systems workload balancing support in Java applications....596
Operation of automatic client reroute for connections to Db2 on Linux, UNIX, and Windows systems from Java clients....597
Operation of alternate group support for connections to Db2 on Linux, UNIX, and Windows systems....600
Application programming requirements for high availability for connections to Db2 on Linux, UNIX, and Windows systems servers....604
Client affinities for Db2 on Linux, UNIX, and Windows systems....605
Java client direct connect support for high availability for connections to Db2 for z/OS servers....608
Configuration of sysplex workload balancing and automatic client reroute for Java clients....610
Example of enabling Db2 for z/OS sysplex workload balancing and automatic client reroute in Java applications....612
Operation of sysplex workload balancing for connections from Java clients to Db2 for z/OS servers....614
Operation of automatic client reroute for connections from Java clients to Db2 for z/OS....615
Application programming requirements for high availability for connections from Java clients to Db2 for z/OS servers....616
Failover support with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS....617

Chapter 14. JDBC and SQLJ connection pooling support....619

Chapter 15. IBM Data Server Driver for JDBC and SQLJ statement caching....621

Chapter 16. IBM Data Server Driver for JDBC and SQLJ type 4 connectivity JDBC and SQLJ distributed transaction support....623
Example of a distributed transaction that uses JTA methods....623

Chapter 17. JDBC and SQLJ global transaction support....627

Chapter 18. Problem diagnosis with the IBM Data Server Driver for JDBC and SQLJ....629
DB2Jcc - IBM Data Server Driver for JDBC and SQLJ diagnostic utility....632
Examples of using configuration properties to start a JDBC trace....635
Example of a trace program under the IBM Data Server Driver for JDBC and SQLJ....637
Techniques for monitoring IBM Data Server Driver for JDBC and SQLJ sysplex support....640

Chapter 19. Tracing IBM Data Server Driver for JDBC and SQLJ C/C++ native driver code....643
db2jcctrace - Format IBM Data Server Driver for JDBC and SQLJ trace data for C/C++ native driver code....643

Chapter 20. System monitoring for the IBM Data Server Driver for JDBC and SQLJ....645

Information resources for Db2 12 for z/OS and related products....647

Notices....649
Programming interface information....650
Trademarks....650
Privacy policy considerations....650

Glossary....653

Index....655

About this information

This information describes Db2 for z/OS support for Java™. This support lets you access relational databases from Java application programs.

Who should read this information

This information is for the following users:

- Db2 for z/OS application developers who are familiar with Structured Query Language (SQL) and who know the Java programming language.
- Db2 for z/OS system programmers who are installing JDBC and SQLJ support.

Db2 Utilities Suite for z/OS

Important: In this Db2 12, Db2 Utilities Suite for z/OS is available as an optional product. You must separately order and purchase a license to such utilities, and discussion of those utility functions in this publication is not intended to otherwise imply that you have a license to them.

Db2 12 utilities can use the DFSORT program regardless of whether you purchased a license for DFSORT on your system. For more information, see the following informational APARs:

- II14047
- II14213
- II13495

Db2 utilities can use IBM® Db2 Sort for z/OS (5655-W42) as an alternative to DFSORT for utility SORT and MERGE functions. Use of Db2 Sort for z/OS requires the purchase of a Db2 Sort for z/OS license. For more information about Db2 Sort for z/OS, see Db2 Sort for z/OS.

Related concepts

Db2 utilities packaging (Db2 Utilities)

Terminology and citations

When referring to a Db2 product other than Db2 for z/OS, this information uses the product's full name to avoid ambiguity.

The following terms are used as indicated:

Db2
Represents either the Db2 licensed program or a particular Db2 subsystem.

IBM rebranded DB2® to Db2, and Db2 for z/OS is the new name of the offering that was previously known as "DB2 for z/OS". For more information, see Revised naming for IBM Db2 family products on IBM z/OS platform. As a result, you might sometimes still see references to the original names, such as "DB2 for z/OS" and "DB2", in different IBM web pages and documents. If the PID, Entitlement Entity, version, modification, and release information match, assume that they refer to the same product.

IBM OMEGAMON® for Db2 Performance Expert on z/OS
Refers to any of the following products:

- IBM IBM OMEGAMON for Db2 Performance Expert on z/OS
- IBM Db2 Performance Monitor on z/OS
- IBM Db2 Performance Expert for Multiplatforms and Workgroups

© Copyright IBM Corp. 1998, 2017

- IBM Db2 Buffer Pool Analyzer for z/OS

C, C++, and C language
Represent the C or C++ programming language.

CICS®
Represents CICS Transaction Server for z/OS.

IMS
Represents the IMS Database Manager or IMS Transaction Manager.

MVS™
Represents the MVS element of the z/OS operating system, which is equivalent to the Base Control Program (BCP) component of the z/OS operating system.

RACF®
Represents the functions that are provided by the RACF component of the z/OS Security Server.

Accessibility features for Db2 12 for z/OS

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, to use information technology products successfully.

Accessibility features

The following list includes the major accessibility features in z/OS products, including Db2 12 for z/OS. These features support:

- Keyboard-only operation.
- Interfaces that are commonly used by screen readers and screen magnifiers.
- Customization of display attributes such as color, contrast, and font size

Tip: IBM Documentation (which includes information for Db2 for z/OS) and its related publications are accessibility-enabled for the IBM Home Page Reader. You can operate all features using the keyboard instead of the mouse.

Keyboard navigation

For information about navigating the Db2 for z/OS ISPF panels using TSO/E or ISPF, refer to the *z/OS TSO/E Primer*, the *z/OS TSO/E User's Guide*, and the *z/OS ISPF User's Guide*. These guides describe how to navigate each interface, including the use of keyboard shortcuts or function keys (PF keys). Each guide includes the default settings for the PF keys and explains how to modify their functions.

Related accessibility information

IBM and accessibility

See the *IBM Accessibility Center* at http://www.ibm.com/able for more information about the commitment that IBM has to accessibility.

How to send your comments about Db2 for z/OS documentation

Your feedback helps IBM to provide quality documentation.

Send any comments about Db2 for z/OS and related product documentation by email to db2zinfo@us.ibm.com.

To help us respond to your comment, include the following information in your email:

- The product name and version
- The address (URL) of the page, for comments about online documentation

- The book name and publication date, for comments about PDF manuals
- The topic or section title
- The specific text that you are commenting about and your comment

Related concepts
About this information (Db2 for z/OS in IBM Documentation)
Related reference
PDF format manuals for Db2 12 for z/OS (Db2 for z/OS in IBM Documentation)

How to read syntax diagrams

Certain conventions apply to the syntax diagrams that are used in IBM documentation.

Apply the following rules when reading the syntax diagrams that are used in Db2 for z/OS documentation:

- Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

  The ►►— symbol indicates the beginning of a statement.

  The —► symbol indicates that the statement syntax is continued on the next line.

  The ►— symbol indicates that a statement is continued from the previous line.

  The —►◄ symbol indicates the end of a statement.
- Required items appear on the horizontal line (the main path).

- Optional items appear below the main path.

  

  If an optional item appears above the main path, that item has no effect on the execution of the statement and is used only for readability.

  

- If you can choose from two or more items, they appear vertically, in a stack.

  If you *must* choose one of the items, one item of the stack appears on the main path.

  

  If choosing one of the items is optional, the entire stack appears below the main path.

  

  If one of the items is the default, it appears above the main path and the remaining choices are shown below.



- An arrow returning to the left, above the main line, indicates an item that can be repeated.



If the repeat arrow contains a comma, you must separate repeated items with a comma.



A repeat arrow above a stack indicates that you can repeat the items in the stack.

- Sometimes a diagram must be split into fragments. The syntax fragment is shown separately from the main syntax diagram, but the contents of the fragment should be read as if they are on the main path of the diagram.

fragment-name



- For some references in syntax diagrams, you must follow any rules described in the description for that diagram, and also rules that are described in other syntax diagrams. For example:
  - For *expression*, you must also follow the rules described in Expressions (Db2 SQL).
  - For references to *fullselect*, you must also follow the rules described in fullselect (Db2 SQL).
  - For references to *search-condition*, you must also follow the rules described in Search conditions (Db2 SQL).
- With the exception of XPath keywords, keywords appear in uppercase (for example, FROM). Keywords must be spelled exactly as shown. XPath keywords are defined as lowercase names, and must be spelled exactly as shown. Variables appear in all lowercase letters (for example, *column-name*). They represent user-supplied names or values.
- If punctuation marks, parentheses, arithmetic operators, or other such symbols are shown, you must enter them as part of the syntax.

Related concepts

Commands in Db2 (Db2 Commands)
SQL: The language of Db2 (Db2 SQL)
Db2 online utilities (Db2 Utilities)
Db2 stand-alone utilities (Db2 Utilities)

Chapter 1. Java application development for IBM data servers

The Db2 and IBM Informix® database systems provide driver support for client applications and applets that are written in Java.

You can access data in Db2 and IBM Informix database systems using JDBC, SQL, or pureQuery®.

JDBC

JDBC is an application programming interface (API) that Java applications use to access relational databases. IBM data server support for JDBC lets you write Java applications that access local Db2 or IBM Informix data or remote relational data on a server that supports DRDA.

SQLJ

SQLJ provides support for embedded static SQL in Java applications. SQLJ was initially developed by IBM, Oracle, and Tandem to complement the dynamic SQL JDBC model with a static SQL model.

For connections to Db2, in general, Java applications use JDBC for dynamic SQL and SQLJ for static SQL.

For connections to IBM Informix, SQL statements in JDBC or SQLJ applications run dynamically.

Because SQLJ can inter-operate with JDBC, an application program can use JDBC and SQLJ within the same unit of work.

pureQuery

pureQuery is a high-performance data access platform that makes it easier to develop, optimize, secure, and manage data access. It consists of:

- Application programming interfaces that are built for ease of use and for simplifying the use of best practices
- Development tools, which are delivered in IBM Data Studio, for Java and SQL development
- A runtime, which is delivered in IBM Optim™ pureQuery Runtime, for optimizing and securing database access and simplifying management tasks

With pureQuery, you can write Java applications that treat relational data as objects, whether that data is in databases or JDBC `DataSource` objects. Your applications can also treat objects that are stored in in-memory Java collections as though those objects are relational data. To query or update your relational data or Java objects, you use SQL.

For more information on pureQuery, see pureQuery data access applications.

R2DBC

R2DBC is an application programming interface (API) that Java reactive applications can use to access a relational database. This API is designed to be non-blocking and asynchronous in nature. The IBM Db2 Java Reactive Driver lets you develop Java reactive applications using the R2DBC API.

For more details on the IBM Db2 Java Reactive Driver, see Java Reactive Driver.

Related concepts

“Supported drivers for JDBC and SQLJ” on page 3

© Copyright IBM Corp. 1998, 2017

The IBM Data Server Driver for JDBC and SQLJ product includes support for two types of JDBC driver architecture. However not all data servers support both types.

Related reference

IBM Data Studio product documentation (IBM Data Studio, IBM Optim Database Administrator, IBM infoSphere Data Architect)

pureQuery data access applications

Chapter 2. Supported drivers for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ product includes support for two types of JDBC driver architecture. However not all data servers support both types.

According to the JDBC specification, there are four types of JDBC driver architectures:

Type 1
Drivers that implement the JDBC API as a mapping to another data access API, such as Open Database Connectivity (ODBC). Drivers of this type are generally dependent on a native library, which limits their portability.

Type 2
Drivers that are written partly in the Java programming language and partly in native code. The drivers use a native client library specific to the data source to which they connect. Because of the native code, their portability is limited.

Type 3
Drivers that use a pure Java client and communicate with a data server using a data-server-independent protocol. The data server then communicates the client's requests to the data source.

Type 4
Drivers that are pure Java and implement the network protocol for a specific data source. The client connects directly to the data source.

Db2 for z/OS supports the IBM Data Server Driver for JDBC and SQLJ, which combines type 2 and type 4 JDBC implementations. The driver is packaged in the following way:

- db2jcc4.jar and sqlj4.zip for JDBC 4.0 or later support

You control the level of JDBC support that you want by specifying the appropriate set of files in the CLASSPATH.

Important: db2jcc.jar and sqlj.zip are no longer supported.

IBM Data Server Driver for JDBC and SQLJ (type 2 and type 4)

The IBM Data Server Driver for JDBC and SQLJ is a single driver that includes JDBC type 2 and JDBC type 4 behavior. When an application loads the IBM Data Server Driver for JDBC and SQLJ, a single driver instance is loaded for type 2 and type 4 implementations. The application can make type 2 and type 4 connections using this single driver instance. The type 2 and type 4 connections can be made concurrently. IBM Data Server Driver for JDBC and SQLJ type 2 driver behavior is referred to as *IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.* IBM Data Server Driver for JDBC and SQLJ type 4 driver behavior is referred to as *IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.*

IBM Data Server Driver for JDBC and SQLJ version 4.*xx* is compliant with JDBC 4.0 or later.

The IBM Data Server Driver for JDBC and SQLJ supports these JDBC and SQLJ functions:

- Version 4.*xx* supports all of the methods that are described in the JDBC 4.0 or later specifications.
- SQLJ application programming interfaces, as defined by the SQLJ standards, for simplified data access from Java applications.
- Connections that are enabled for connection pooling. WebSphere® Application Server or another application server does the connection pooling.
- Connections to a data server from Java user-defined functions and stored procedures use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity only. Applications that call user-defined functions or stored procedures can use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to connect to a data server.
- Support for distributed transaction management. This support implements the Java 2 Platform, Enterprise Edition (J2EE) Java Transaction Service (JTS) and Java Transaction API (JTA) specifications,

© Copyright IBM Corp. 1998, 2017

which conform to the X/Open standard for distributed transactions (*Distributed Transaction Processing: The XA Specification*, available from http://www.opengroup.org) (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS environment, Version 7 or later, or to Db2 on Linux®, UNIX, and Windows systems).

In general, you should use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity for Java programs that run on the same z/OS system or IBM Z logical partition (LPAR) as the target Db2 subsystem. Use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity for Java programs that run on a different z/OS system or LPAR from the target Db2 subsystem.

For z/OS systems or LPARs that do not have Db2 for z/OS, the z/OS Application Connectivity to Db2 for z/OS optional feature can be installed to provide IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to a Db2 on Linux, UNIX, and Windows systems data server.

To use the IBM Data Server Driver for JDBC and SQLJ, you need Java 2 Technology Edition, V5 or later.

Related concepts

"Environment variables for the z/OS Application Connectivity to Db2 for z/OS feature" on page 553
You need to set environment variables so that the operating system can locate the z/OS Application Connectivity to Db2 for z/OS feature.

How to find the IBM Data Server Driver for JDBC and SQLJ version

To determine the version of the IBM Data Server Driver for JDBC and SQLJ, run the DB2Jcc utility with the -version parameter.

Enter this text on the client command line.

```
java com.ibm.db2.jcc.DB2Jcc -version
```

Related reference

"DB2Jcc - IBM Data Server Driver for JDBC and SQLJ diagnostic utility" on page 632
DB2Jcc verifies that a data server is configured for database access.

Db2 for z/OS and IBM Data Server Driver for JDBC and SQLJ versions

Db2 for z/OS APARs are used to ship the IBM Data Server Driver for JDBC and SQLJ.

Important: The JDBC 3 version of the IBM Data Server Driver for JDBC and SQLJ is no longer supported.

IBM Data Server Driver for JDBC and SQLJ 4.*xx* versions and Db2 for z/OS APARs

The following table lists the major 4.*xx* versions of the IBM Data Server Driver for JDBC and SQLJ and the Db2 for z/OS Version 13 APAR that delivered the initial release of each version.

Table 1. IBM Data Server Driver for JDBC and SQLJ 4.xx versions and corresponding Db2 for z/OS Version 13 APARs

IBM Data Server Driver for JDBC and SQLJ version	Db2 for z/OS Version 13 APAR/PTF
4.32.49	PH56221/UI93576
4.32.46	PH55284/UI92488
4.32.45	PH51779/UI92024
4.31.25	PH48861/UI83244
4.31.18	PH47828/UI81607

The following table lists the major 4.*xx* versions of the IBM Data Server Driver for JDBC and SQLJ and the Db2 for z/OS Version 12 APAR that delivered the initial release of each version.

Table 2. IBM Data Server Driver for JDBC and SQLJ 4.xx versions and corresponding Db2 for z/OS Version 12 APARs

IBM Data Server Driver for JDBC and SQLJ version	Db2 for z/OS Version 12 APAR/PTF
4.32.49	PH56221/UI93575
4.32.46	PH55284/UI92489
4.32.45	PH51779/UI92023
4.31.25	PH48861/UI83243
4.31.18	PH47828/UI81606
4.31.15	PH43423/UI80323
4.29.27	PH40658/UI77245
4.28.11	PH32181/UI72953
4.27.26	PH28350/UI71213
4.26.18	PH22490/UI68263
4.26.16	PH17211/UI65729
4.25.21	PH14604/UI64434
4.25.17	PH09452/UI61809
4.25.14	PH05977/UI60494
4.24	PI98598/UI59279
4.23	PI92195/UI55687
4.22	PI76338/UI47392
4.21	PI67610/UI44315
4.19.66	PI59547/UI39908

IBM Data Server Driver for JDBC and SQLJ 3.*xx* versions and Db2 for z/OS Version 12 APARs

The following table lists the major 3.*xx* versions of the IBM Data Server Driver for JDBC and SQLJ and the Db2 for z/OS Version 12 APAR that delivered the initial release of each version.

Table 3. IBM Data Server Driver for JDBC and SQLJ 3.xx versions and corresponding Db2 for z/OS Version 12 APARs

IBM Data Server Driver for JDBC and SQLJ version	Db2 for z/OS Version 12 APAR/PTF
3.72.54	PH05988/UI60497
3.72.53	PI98662/UI59282
3.72.45	PI92198/UI55692
3.72.30	PI76340/UI47363
3.71	PI67609/UI44298

Table 3. IBM Data Server Driver for JDBC and SQLJ 3.xx versions and corresponding Db2 for z/OS Version 12 APARs (continued)

IBM Data Server Driver for JDBC and SQLJ version	Db2 for z/OS Version 12 APAR/PTF
3.69.66	PI59538/UI39912

Compatibility of Db2 for z/OS versions and IBM Data Server Driver for JDBC and SQLJ versions for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS

For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, the driver can be used with certain other versions of a Db2 for z/OS data server than the version for which the driver was shipped. See IBM Data Server Driver for JDBC and SQLJ Driver Versions and Downloads for Db2 z/OS for information on the minimum and maximum driver versions that are compatible with each Db2 for z/OS version.

Compatibility of Db2 for z/OS versions and IBM Data Server Driver for JDBC and SQLJ versions for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, a driver version must be used with the version and PTF level of the Db2 for z/OS data server for which the driver was shipped.

Related information

IBM Data Server Driver for JDBC and SQLJ Versions and APARs

IBM Data Server Driver for JDBC and SQLJ versions and Db2 or Db2 Connect levels

Each version and release of Db2 on Linux, UNIX, and Windows systems is shipped with a JDBC 4 version of the IBM Data Server Driver for JDBC and SQLJ.

Important: Starting with the version of the IBM Data Server Driver for JDBC and SQLJ that is delivered with Db2 Version 11.5, the JDBC 3 version of the driver is not supported, and the db2jcc.jar and sqlj.zip files are not included.

The following table lists:

- IBM Data Server Driver for JDBC and SQLJ versions
- The Db2 or Db2 Connect level in which each driver version was shipped. The *level* consists of a version and release, and sometimes also a modification and fix pack. The level is in one of the following forms:

```
Version vv.rel Modification mod Fix Pack fp
Version vv.rel Modification mod Fix Pack fp
Version vv.rel Fix Pack fp
Version vv.rel
```

Table 4. Db2 or Db2 Connect levels and IBM Data Server Driver for JDBC and SQLJ versions

Db2 or Db2 Connect level	IBM Data Server Driver for JDBC and SQLJ version"1" on page 8
Version 11.5 Modification 9 Fix Pack 0	4.33.*xx*
Version 11.5 Modification 8 Fix Pack 0	4.32.*xx*
Version 11.5 Modification 7 Fix Pack 0	4.31.*xx*
Db2 Version 11.5 Modification 6 Fix Pack 0	4.29.*xx*

Table 4. Db2 or Db2 Connect levels and IBM Data Server Driver for JDBC and SQLJ versions (continued)

Db2 or Db2 Connect level	IBM Data Server Driver for JDBC and SQLJ version"1" on page 8
Db2 Version 11.5 Modification 5 Fix Pack 0	4.28.*xx*
Db2 Version 11.5 Modification 4 Fix Pack 0	4.27.*xx*
Db2 Version 11.5 Fix Pack 0	4.26.*xx*
Db2 Version 11.1 Modification 4 Fix Pack 4	4.25.*xx*
Db2 Version 11.1 Modification 3 Fix Pack 3	3.72.*xx*, 4.24.*xx*
Db2 Version 11.1 Modification 2 Fix Pack 2	3.72.*xx*, 4.23.*xx*
Db2 Version 11.1 Modification 1 Fix Pack 1	3.72.*xx*, 4.22.*xx*
Db2 Version 11.1	3.71.*xx*, 4.21.*xx*
Db2 Version 10.5 Fix Pack 5	3.69.*xx*, 4.19.*xx*
Db2 Cancun Release 10.5.0.4	3.68.*xx*, 4.18.*xx*
Db2 Version 10.5 Fix Pack 2	3.67.*xx*, 4.17.*xx*
Db2 Version 10.5	3.66.*xx*, 4.16.*xx*
Db2 Version 10.1 Fix Pack 2	3.65.*xx*, 4.15.*xx*
Db2 Version 10.1 Fix Pack 1	3.64.*xx*, 4.14.*xx*
Db2 Version 10.1	3.63.*xx*, 4.13.*xx*
Db2 Version 9.7 Fix Pack 6	3.64.*xx*, 4.14.*xx*
Db2 Version 9.7 Fix Pack 5	3.63.*xx*, 4.13.*xx*
Db2 Version 9.7 Fix Pack 4	3.62.*xx*, 4.12.*xx*
Db2 Version 9.7 Fix Pack 2	3.59.*xx*, 4.9.*xx*
Db2 Version 9.7 Fix Pack 1	3.58.*xx*, 4.8.*xx*
Db2 Version 9.7	3.57.*xx*, 4.7.*xx*
Db2 Version 9.5 Fix Pack 7	3.61.*xx*, 4.8.*xx*
Db2 Version 9.5 Fix Pack 6	3.58.*xx*, 4.8.*xx*
Db2 Version 9.5 Fix Pack 5	3.57.*xx*, 4.7.*xx*
Db2 Version 9.5 Fix Pack 3 and Fix Pack 4	3.53.*xx*, 4.3.*xx*
Db2 Version 9.5 Fix Pack 2	3.52.*xx*, 4.2.*xx*
Db2 Version 9.5 Fix Pack 1	3.51.*xx*, 4.1.*xx*
Db2 Version 9.5	3.50.*xx*, 4.0.*xx*
Db2 Version 9.1 Fix Pack 5 and later	3.7.*xx*
Db2 Version 9.1 Fix Pack 4	3.6.*xx*
Db2 Version 9.1 Fix Pack 3	3.4.*xx*
Db2 Version 9.1 Fix Pack 2	3.3.*xx*
Db2 Version 9.1 Fix Pack 1	3.2.*xx*
Db2 Version 9.1	3.1.*xx*

Table 4. Db2 or Db2 Connect levels and IBM Data Server Driver for JDBC and SQLJ versions (continued)

Db2 or Db2 Connect level	IBM Data Server Driver for JDBC and SQLJ version"1" on page 8

Note:

1. All driver versions are of the form *n.m.xx*. *n.m* stays the same within a GA level or a fix pack level. *xx* changes when a new version of the IBM Data Server Driver for JDBC and SQLJ is introduced through an APAR fix.

You can find more detailed information about IBM Data Server Driver for JDBC and SQLJ and Db2 or Db2 Connect levels at the following URL:

```
http://www.ibm.com/support/docview.wss?&uid=swg21363866
```

Compatibility of Db2 levels and IBM Data Server Driver for JDBC and SQLJ versions for connections to Db2 on Linux, UNIX, and Windows systems

To ensure compatibility, you should connect to a Db2 data server using the version of the IBM Data Server Driver for JDBC and SQLJ that was shipped with that Db2 level. However, you can connect to certain other levels of Db2 than the level with which the driver was shipped.

A Db2 product level is of the format VV.RR.MM.FF where:

- VV is the version number.
- RR is the release number.
- MM is the modification number.
- FF is the fix pack number.

A version of the IBM Data Server Driver for JDBC and SQLJ is compatible with:

- The Db2 version and release (VV.RR) in which that driver was shipped.
- Any *in-support* Db2 version and release that is lower than the version and release in which the driver version was shipped. See End-of-support dates for Db2 data servers on Linux, UNIX, and Windows systems for information on which Db2 versions and releases are supported.
- Any Db2 version and release that is higher than the version and release in which the driver version was shipped, if the Java application uses no features of the higher Db2 version and release.

For example, IBM Data Server Driver for JDBC and SQLJ version 4.31.*xx* is shipped with Db2 11.5.7.0, so the Db2 version and release with which the driver is shipped is 11.5. Assume that Db2 product levels with a version and release of 11.5 and of 11.1 are supported. Driver version 4.31.*xx* is then compatible with Db2 version and release 11.5 and Db2 version and release 11.1. Driver version 4.31.*xx* is also compatible with any Db2 product level with a version and release that is higher than 11.5, if the Java application uses no features of the higher product level.

Chapter 3. JDBC application programming

Writing a JDBC application has much in common with writing an SQL application in any other language.

In general, you need to do the following things:

- Access the Java packages that contain JDBC methods.
- Declare variables for sending data to or retrieving data from data server tables.
- Connect to a data source.
- Execute SQL statements.
- Handle SQL errors and warnings.
- Disconnect from the data source.

Although the tasks that you need to perform are similar to those in other languages, the way that you execute those tasks is somewhat different.

Example of a simple JDBC application

A simple JDBC application demonstrates the basic elements that JDBC applications need to include.

Figure 1. Simple JDBC application

```
import java.sql.*;                                                          1

public class EzJava
{
  public static void main(String[] args)
  {
    String urlPrefix = "jdbc:db2:";
    String url;
    String user;
    String password;
    String empNo;                                                           2
    Connection con;
    Statement stmt;
    ResultSet rs;

    System.out.println ("**** Enter class EzJava");

    // Check the that first argument has the correct form for the portion
    // of the URL that follows jdbc:db2:,
    // as described
    // in the Connecting to a data source using the DriverManager
    // interface with the IBM Data Server Driver for JDBC and SQLJ topic.
    // For example, for IBM Data Server Driver for
    // JDBC and SQLJ type 2 connectivity,
    // args[0] might be MVS1DB2M. For
    // type 4 connectivity, args[0] might
    // be //stlmvs1:10110/MVS1DB2M.


    if (args.length!=3)
    {
      System.err.println ("Invalid value. First argument appended to "+
       "jdbc:db2: must specify a valid URL.");
      System.err.println ("Second argument must be a valid user ID.");
      System.err.println ("Third argument must be the password for the user ID.");
      System.exit(1);
    }
    url = urlPrefix + args[0];
    user = args[1];
    password = args[2];
    try
    {
      // Load the driver
      Class.forName("com.ibm.db2.jcc.DB2Driver");                           3a
      System.out.println("**** Loaded the JDBC driver");

      // Create the connection using the IBM Data Server Driver for JDBC and SQLJ
```

© Copyright IBM Corp. 1998, 2017

```
      con = DriverManager.getConnection (url, user, password);              3b
      // Commit changes manually
      con.setAutoCommit(false);
      System.out.println("**** Created a JDBC connection to the data source");

      // Create the Statement
      stmt = con.createStatement();                                         4a
      System.out.println("**** Created JDBC Statement object");

      // Execute a query and generate a ResultSet instance
      rs = stmt.executeQuery("SELECT EMPNO FROM EMPLOYEE");                 4b
      System.out.println("**** Created JDBC ResultSet object");

      // Print all of the employee numbers to standard output device
      while (rs.next()) {
        empNo = rs.getString(1);
        System.out.println("Employee number = " + empNo);
      }
      System.out.println("**** Fetched all rows from JDBC ResultSet");
      // Close the ResultSet
      rs.close();
      System.out.println("**** Closed JDBC ResultSet");

      // Close the Statement
      stmt.close();
      System.out.println("**** Closed JDBC Statement");

      // Connection must be on a unit-of-work boundary to allow close
      con.commit();
      System.out.println ( "**** Transaction committed" );

      // Close the connection
      con.close();                                                          6
      System.out.println("**** Disconnected from data source");

      System.out.println("**** JDBC Exit from class EzJava - no errors");

    }

    catch (ClassNotFoundException e)
    {
      System.err.println("Could not load JDBC driver");
      System.out.println("Exception: " + e);
      e.printStackTrace();
    }

    catch(SQLException ex)                                                  5
    {
      System.err.println("SQLException information");
      while(ex!=null) {
        System.err.println ("Error msg: " + ex.getMessage());
        System.err.println ("SQLSTATE: " + ex.getSQLState());
        System.err.println ("Error code: " + ex.getErrorCode());
        ex.printStackTrace();
        ex = ex.getNextException(); // For drivers that support chained exceptions
      }
    }
  }  // End main
}    // End EzJava
```

Notes to Figure 1 on page 9:

Note	Description
1	This statement imports the java.sql package, which contains the JDBC core API. For information on other Java packages that you might need to access, see "Java packages for JDBC support".
2	`String` variable empNo performs the function of a host variable. That is, it is used to hold data retrieved from an SQL query. See "Variables in JDBC applications" for more information.
3a and 3b	These two sets of statements demonstrate how to connect to a data source using one of two available interfaces. See "How JDBC applications connect to a data source" for more details. Step 3a (loading the JDBC driver) is not necessary if you use JDBC 4.0 or later.

Note	Description
4a and 4b	These two sets of statements demonstrate how to perform a SELECT in JDBC. For information on how to perform other SQL operations, see "JDBC interfaces for executing SQL".
5	This `try/catch` block demonstrates the use of the `SQLException` class for SQL error handling. For more information on handling SQL errors, see "Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ". For information on handling SQL warnings, see "Handling an SQLWarning under the IBM Data Server Driver for JDBC and SQLJ".
6	This statement disconnects the application from the data source. See "Disconnecting from data sources in JDBC applications".

Related concepts

"How JDBC applications connect to a data source" on page 11
Before you can execute SQL statements in any SQL program, you must be connected to a data source.

"JDBC interfaces for executing SQL" on page 30
You execute SQL statements in a traditional SQL program to update data in tables, retrieve data from the tables, or call stored procedures. To perform the same functions in a JDBC program, you invoke methods.

"Variables in JDBC applications" on page 28
As in any other Java application, when you write JDBC applications, you declare variables. In Java applications, those variables are known as Java identifiers.

"Java packages for JDBC support" on page 25
Before you can invoke JDBC methods, you need to be able to access all or parts of various Java packages that contain those methods.

Related tasks

"Handling an SQLWarning under the IBM Data Server Driver for JDBC and SQLJ" on page 113
Unlike SQL errors, SQL warnings do not cause JDBC methods to throw exceptions. Instead, the `Connection`, `Statement`, `PreparedStatement`, `CallableStatement`, and `ResultSet` classes contain `getWarnings` methods, which you need to invoke after you execute SQL statements to determine whether any SQL warnings were generated.

"Disconnecting from data sources in JDBC applications" on page 117
When you have finished with a connection to a data source, it is *essential* that you close the connection to the data source. Doing this releases the `Connection` object's database and JDBC resources immediately.

How JDBC applications connect to a data source

Before you can execute SQL statements in any SQL program, you must be connected to a data source.

The IBM Data Server Driver for JDBC and SQLJ supports type 2 and type 4 connectivity. Connections to Db2 databases can use type 2 or type 4 connectivity. Connections to IBM Informix databases can use type 4 connectivity.

The following figure shows how a Java application connects to a data source using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity. JDBC method calls in the Java application are sent to the driver. The driver converts JDBC calls into native calls for the local data source. Remote calls are passed to the remote data source.



*Java byte code executed under JVM, and native code

Figure 2. Java application flow for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity

The following figure shows how a Java application connects to a data source using IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. JDBC method calls in the Java application are sent to the driver. The driver converts JDBC calls into the network protocol for the data source.



*Java byte code executed under JVM

Figure 3. Java application flow for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity

Related tasks

"Connecting to a data source using SQLJ" on page 121
In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

"Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ" on page 13

A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ

A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

Procedure

The steps for establishing a connection are:

1. Load the JDBC driver by invoking the `Class.forName` method.

   If you are using JDBC 4.0 or later, you do not need to explicitly load the JDBC driver.

   For the IBM Data Server Driver for JDBC and SQLJ, you load the driver by invoking the `Class.forName` method with the following argument:

   ```
   com.ibm.db2.jcc.DB2Driver
   ```

   For compatibility with previous JDBC drivers, you can use the following argument instead:

   ```
   COM.ibm.db2os390.sqlj.jdbc.DB2SQLJDriver
   ```

   The following code demonstrates loading the IBM Data Server Driver for JDBC and SQLJ:

   ```
   try {
     // Load the IBM Data Server Driver for JDBC and SQLJ with DriverManager
     Class.forName("com.ibm.db2.jcc.DB2Driver");
   } catch (ClassNotFoundException e) {
       e.printStackTrace();
   }
   ```

   The `catch` block is used to print an error if the driver is not found.
2. Connect to a data source by invoking the `DriverManager.getConnection` method.

   You can use one of the following forms of `getConnection`:

   ```
   getConnection(String url);
   getConnection(String url, user, password);
   getConnection(String url, java.util.Properties info);
   ```

   For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, the `getConnection` method must specify a user ID and password, through parameters or through property values.

   The *url* argument represents a data source, and indicates what type of JDBC connectivity you are using.

   The *info* argument is an object of type `java.util.Properties` that contains a set of driver properties for the connection. Specifying the *info* argument is an alternative to specifying *property=value;* strings in the URL. See "Properties for the IBM Data Server Driver for JDBC and SQLJ" for the properties that you can specify.

   There are several ways to specify a user ID and password for a connection:

   - Use the form of the `getConnection` method that specifies *url* with `property=`*value*; clauses, and include the user and password properties in the URL.
   - Use the form of the `getConnection` method that specifies *user* and *password*.
   - Use the form of the `getConnection` method that specifies *info*, after setting the user and password properties in a `java.util.Properties` object.

Examples

Example: Establishing a connection and setting the user ID and password in a URL:

```
String url = "jdbc:db2://myhost:5021/mydb:" +
  "user=dbadm;password=dbadm;";

                                          // Set URL for data source
Connection con = DriverManager.getConnection(url);
                                          // Create connection
```

Example: Establishing a connection and setting the user ID and password in user and password parameters:

```
String url = "jdbc:db2://myhost:5021/mydb";
                                          // Set URL for data source
String user = "dbadm";
String password = "dbadm";
Connection con = DriverManager.getConnection(url, user, password);
                                          // Create connection
```

Example: Establishing a connection and setting the user ID and password in a `java.util.Properties` object:

```
Properties properties = new Properties(); // Create Properties object
properties.put("user", "dbadm");          // Set user ID for connection
properties.put("password", "dbadm");      // Set password for connection
String url = "jdbc:db2://myhost:5021/mydb";
                                          // Set URL for data source
Connection con = DriverManager.getConnection(url, properties);
                                          // Create connection
```

URL format for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity

If you are using type 4 connectivity in your JDBC application, and you are making a connection using the `DriverManager` interface, you need to specify a URL in the `DriverManager.getConnection` call that indicates type 4 connectivity.

IBM Data Server Driver for JDBC and SQLJ type 4 connectivity URL syntax



connection-options



special-registers



global-variables



query-acceleration



Notes:

[1] *property=value* pairs, the special-registers string, and the global-variables string can be specified in any order.

IBM Data Server Driver for JDBC and SQLJ type 4 connectivity URL option descriptions

The parts of the URL have the following meanings:

jdbc:db2: or jdbc:db2j:net:
The meanings of the initial portion of the URL are:

jdbc:db2:
Indicates that the connection is to a Db2 for z/OS, Db2 on Linux, UNIX, and Windows systems.

jdbc:db2: can also be used for a connection to an IBM Informix database, for application portability.

jdbc:db2j:net:
Indicates that the connection is to a remote IBM Cloudscape server.

jdbc:ibmdb:
Indicates that the connection is to any IBM Data Server that the IBM Data Server Driver for JDBC and SQLJ supports.

jdbc:ids:
Indicates that the connection is to an IBM Informix data source. jdbc:informix-sqli: also indicates that the connection is to an IBM Informix data source, but jdbc:ids: should be used.

server
The domain name or IP address of the data source.

port
The TCP/IP server port number that is assigned to the data source. This is an integer between 0 and 65535. The default is 446.

database
A name for the data source.

- If the connection is to a Db2 for z/OS server, *database* is the Db2 location name that is defined during installation. All characters in the Db2 location name must be uppercase characters.

  The IBM Data Server Driver for JDBC and SQLJ does not convert lowercase characters in the database value to uppercase for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

  You can determine the location name by executing the following SQL statement on the server:

  ```
  SELECT CURRENT SERVER FROM SYSIBM.SYSDUMMY1;
  ```

- If the connection is to a Db2 for z/OS server or a Db2 for IBM i server, all characters in *database* must be uppercase characters.
- If the connection is to a Db2 on Linux, UNIX, and Windows systems server, *database* is the database name that is defined during installation.
- If the connection is to an IBM Informix server, *database* is the database name. The name is case-insensitive. The server converts the name to lowercase.

- If the connection is to an IBM Cloudscape server, the *database* is the fully-qualified name of the file that contains the database. This name must be enclosed in double quotation marks ("). For example:

```
"c:/databases/testdb"
```

***property=value*;**
A property and its value for the JDBC connection. You can specify one or more property and value pairs. Each property and value pair, including the last one, must end with a semicolon (;). Do not include spaces or other white space characters anywhere within the list of property and value strings.

Some properties with an int data type have predefined constant field values. You must resolve constant field values to their integer values before you can use those values in the *url* parameter. For example, you cannot use com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL in a *url* parameter. However, you can build a URL string that includes com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL, and assign the URL string to a String variable. Then you can use the String variable in the *url* parameter:

```
String url =
 "jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1" +
 ":user=dbadm;password=dbadm;" +
 "traceLevel=" +
 (com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL) + ";";
 Connection con =
   java.sql.DriverManager.getConnection(url);
```

specialRegisters=*special-register-name=special-register-value,...special-register-name=special-register-value*
A list of special register settings for the JDBC connection. You can specify one or more special register name and value pairs. Special register name and value pairs must be delimited by commas (,). The last pair must end with a semicolon (;). For example:

```
String url =
 "jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1" +
 ":user=dbadm;password=dbadm;" +
 "specialRegisters=CURRENT_PATH=SYSIBM,CURRENT CLIENT_USERID=test" + ";";
Connection con =
   java.sql.DriverManager.getConnection(url);
```

For special registers that can be set through IBM Data Server Driver for JDBC and SQLJ `Connection` properties, if you set a special register value in a URL string using specialRegisters, and you also set that value in a `java.util.Properties` object using the following form of `getConnection`, the special register is set to the value from the URL string.

```
getConnection(String url, java.util.Properties info);
```

You can specify only one value for each special register using the specialRegisters parameter. For special registers that take multiple values, such as CURRENT PATH, CURRENT PACKAGE PATH, CURRENT PACKAGESET, you can specify multiple values for a special register by using the `DataSource` interface and the `DB2DataSource.setSpecialRegisters` method.

globalSessionVariables=*session-variable-name=session-variable-value,...session-variable-name=session-variable-value*
A list of session variable settings for the JDBC connection. You can specify one or more session variable name and value pairs.

Session variable settings apply only to Db2 for z/OS Version 11 or later data servers.

Session variable name and value pairs must be delimited by commas (,). The last pair must end with a semicolon (;). For example:

```
String url =
     "jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1" +
  ":user=dbadm;password=dbadm;" +
  "globalSessionVariables=SESSION.TEST=FAILED,SYSIBMADM.GET_ARCHIVE=Y" + ";";
```

```
Connection con =
  java.sql.DriverManager.getConnection(url);
```

queryAcceleration=*value*;
Changes the value of the CURRENT QUERY ACCELERATION special register.

Possible values are:

NONE
Specifies that no query acceleration is done.

ENABLE
Specifies that queries are accelerated only if Db2 determines that it is advantageous to do so. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 returns a negative SQLCODE to the application.

ENABLE WITH FAILBACK
Specifies that queries are accelerated only if Db2 determines that it is advantageous to do so. If the accelerator returns an error during the PREPARE or first OPEN for the query, Db2 executes the query without the accelerator. If the accelerator returns an error during a FETCH or a subsequent OPEN, Db2 returns the error to the user, and does not execute the query.

ELIGIBLE
Specifies that queries are accelerated if they are eligible for acceleration. Db2 does not use cost information to determine whether to accelerate the queries. Queries that are not eligible for acceleration are executed by Db2. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 returns a negative SQLCODE to the application.

ALL
Specifies that queries are accelerated if they are eligible for acceleration. Db2 does not use cost information to determine whether to accelerate the queries. Queries that are not eligible for acceleration are not executed by Db2, and an SQL error is returned. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 returns a negative SQLCODE to the application.

Related reference
"DB2DataSource class" on page 437
The `com.ibm.db2.jcc.DB2DataSource` class extends the `DB2BaseDataSource` class, and implements the `javax.sql.DataSource`, `java.io.Serializable`, and `javax.naming.Referenceable` interfaces.

URL format for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity

If you are using type 2 connectivity in your JDBC application, and you are making a connection using the `DriverManager` interface, you need to specify a URL in the `DriverManager.getConnection` call that indicates type 2 connectivity.

IBM Data Server Driver for JDBC and SQLJ type 2 connectivity URL syntax



connection-options



special-registers



global-variables



query-acceleration



Notes:

[1] *property=value* pairs, the special-registers string, and the global-variables string can be specified in any order.

IBM Data Server Driver for JDBC and SQLJ type 2 connectivity URL options descriptions

The parts of the URL have the following meanings:

jdbc:db2: or jdbc:db2os390: or jdbc:db2os390sqlj: or jdbc:default:connection
The meanings of the initial portion of the URL are:

jdbc:db2: or jdbc:db2os390: or jdbc:db2os390sqlj:
Indicates that the connection is to a Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems server. jdbc:db2os390: and jdbc:db2os390sqlj: are for compatibility of programs that were written for older drivers, and apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS only.

jdbc:default:connection
Indicates that the URL is for a connection to the local subsystem through a Db2 thread that is controlled by CICS, IMS, or the Java stored procedure environment.

database
A name for the database server.

- *database* is a location name that is defined in the SYSIBM.LOCATIONS catalog table.

  All characters in the Db2 location name must be uppercase characters. However, for a connection to a Db2 for z/OS server, the IBM Data Server Driver for JDBC and SQLJ converts lowercase characters in the database value to uppercase.

***property=value*;**
A property and its value for the JDBC connection. You can specify one or more property and value pairs. Each property and value pair, including the last one, must end with a semicolon (;). Do not include spaces or other white space characters anywhere within the list of property and value strings.

Some properties with an int data type have predefined constant field values. You must resolve constant field values to their integer values before you can use those values in the *url* parameter. For example, you cannot use com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL in a *url* parameter. However, you can build a URL string that includes com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL, and assign the URL string to a String variable. Then you can use the String variable in the *url* parameter:

```
String url =
 "jdbc:db2:STLEC1" +
```

```
    ":user=dbadm;password=dbadm;" +
    "traceLevel=" +
    (com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL) + ";";
    Connection con =
      java.sql.DriverManager.getConnection(url);
```

specialRegisters=*special-register-name=special-register-value,...special-register-name=special-register-value*

A list of special register settings for the JDBC connection. You can specify one or more special register name and value pairs. Special register name and value pairs must be delimited by commas (,). The last pair must end with a semicolon (;). For example:

```
String url =
  "jdbc:db2:STLEC1" +
  ":user=dbadm;password=dbadm;" +
  "specialRegisters=CURRENT_PATH=SYSIBM,CURRENT CLIENT_USERID=test" + ";";
Connection con =
  java.sql.DriverManager.getConnection(url);
```

For special registers that can be set through IBM Data Server Driver for JDBC and SQLJ `Connection` properties, if you set a special register value in a URL string using specialRegisters, and you also set that value in a `java.util.Properties` object using the following form of `getConnection`, the special register is set to the value from the URL string.

```
getConnection(String url, java.util.Properties info);
```

If you specify a special register that is supported on the data server, but you specify a value that is not supported on the data server, the IBM Data Server Driver for JDBC and SQLJ returns an error. If you specify a special register that is not supported on the data server, the driver returns a warning.

You can specify only one value for each special register using the specialRegisters parameter. For special registers that take multiple values, such as CURRENT PATH, CURRENT PACKAGE PATH, CURRENT PACKAGESET, you can specify multiple values for a special register by using the `DataSource` interface and the `DB2DataSource.setSpecialRegisters` method.

globalSessionVariables=*global-variable-name=global-variable-value,...global-variable-name=global-variable-value*

A list of global variable settings for the JDBC connection. You can specify one or more global variable name and value pairs.

global variable settings apply only to Db2 for z/OS Version 11 or later data servers.

global variable name and value pairs must be delimited by commas (,). The last pair must end with a semicolon (;). For example:

```
String url =
  "jdbc:db2:STLEC1" +
  ":user=dbadm;password=dbadm;" +
  "globalSessionVariables=SESSION.TEST=FAILED,SYSIBMADM.GET_ARCHIVE=Y" + ";";
Connection con =
  java.sql.DriverManager.getConnection(url);
```

queryAcceleration=*value*;

Changes the value of the CURRENT QUERY ACCELERATION special register.

Possible values are:

NONE
Specifies that no query acceleration is done.

ENABLE
Specifies that queries are accelerated only if Db2 determines that it is advantageous to do so. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 returns a negative SQLCODE to the application.

ENABLE WITH FAILBACK
Specifies that queries are accelerated only if Db2 determines that it is advantageous to do so. If the accelerator returns an error during the PREPARE or first OPEN for the query, Db2 executes the query without the accelerator. If the accelerator returns an error during a FETCH or a subsequent OPEN, Db2 returns the error to the user, and does not execute the query.

ELIGIBLE
Specifies that queries are accelerated if they are eligible for acceleration. Db2 does not use cost information to determine whether to accelerate the queries. Queries that are not eligible for acceleration are executed by Db2. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 returns a negative SQLCODE to the application.

ALL
Specifies that queries are accelerated if they are eligible for acceleration. Db2 does not use cost information to determine whether to accelerate the queries. Queries that are not eligible for acceleration are not executed by Db2, and an SQL error is returned. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 returns a negative SQLCODE to the application.

Related reference
"DB2DataSource class" on page 437
The `com.ibm.db2.jcc.DB2DataSource` class extends the `DB2BaseDataSource` class, and implements the `javax.sql.DataSource`, `java.io.Serializable`, and `javax.naming.Referenceable` interfaces.

Connecting to a data source using the DataSource interface

If your applications need to be portable among data sources, you should use the `DataSource` interface.

About this task

Using `DriverManager` to connect to a data source reduces portability because the application must identify a specific JDBC driver class name and driver URL. The driver class name and driver URL are specific to a JDBC vendor, driver implementation, and data source.

When you connect to a data source using the `DataSource` interface, you use a `DataSource` object.

The simplest way to use a `DataSource` object is to create and use the object in the same application, as you do with the `DriverManager` interface. However, this method does not provide portability.

The best way to use a `DataSource` object is for your system administrator to create and manage it separately, using WebSphere Application Server or some other tool. The program that creates and manages a `DataSource` object also uses the Java Naming and Directory Interface (JNDI) to assign a logical name to the `DataSource` object. The JDBC application that uses the `DataSource` object can then refer to the object by its logical name, and does not need any information about the underlying data source. In addition, your system administrator can modify the data source attributes, and you do not need to change your application program.

To learn more about using WebSphere to deploy DataSource objects, go to this URL on the web:

```
http://www.ibm.com/software/webservers/appserv/
```

To learn about deploying DataSource objects yourself, see "Creating and deploying DataSource objects".

You can use the `DataSource` interface and the `DriverManager` interface in the same application, but for maximum portability, it is recommended that you use only the `DataSource` interface to obtain connections.

Procedure

To obtain a connection using a `DataSource` object that the system administrator has already created and assigned a logical name to, follow these steps:

1. From your system administrator, obtain the logical name of the data source to which you need to connect.
2. Create a `Context` object to use in the next step. The `Context` interface is part of the Java Naming and Directory Interface (JNDI), not JDBC.
3. In your application program, use JNDI to get the `DataSource` object that is associated with the logical data source name.
4. Use the `DataSource.getConnection` method to obtain the connection.

   You can use one of the following forms of the `getConnection` method:

   ```
   getConnection();
   getConnection(String user, String password);
   ```

   Use the second form if you need to specify a user ID and password for the connection that are different from the ones that were specified when the `DataSource` was deployed.

Examples

Example of obtaining a connection using a `DataSource` object that was created by the system administrator: In this example, the logical name of the data source that you need to connect to is `jdbc/sampledb`. The numbers to the right of selected statements correspond to the previously-described steps.

```
import java.sql.*;
import javax.naming.*;
import javax.sql.*;
…
Context ctx=new InitialContext();                          2
DataSource ds=(DataSource)ctx.lookup("jdbc/sampledb");     3
Connection con=ds.getConnection();                         4
```

Figure 4. Obtaining a connection using a DataSource object

Example of creating and using a `DataSource` object in the same application:

Figure 5. Creating and using a DataSource object in the same application

```
import java.sql.*;        // JDBC base
import javax.sql.*;       // Additional methods for JDBC
import com.ibm.db2.jcc.*; // IBM Data Server Driver for JDBC and SQLJ  1
                          // interfaces
DB2SimpleDataSource dbds=new DB2SimpleDataSource();            2
dbds.setDatabaseName("dbloc1");                                3
                          // Assign the location name
dbds.setDescription("Our Sample Database");
                          // Description for documentation
dbds.setUser("john");
                          // Assign the user ID
dbds.setPassword("dbadm");
                          // Assign the password
Connection con=dbds.getConnection();                           4
                          // Create a Connection object
```

Note	Description
1	Import the package that contains the implementation of the DataSource interface.
2	Creates a `DB2SimpleDataSource` object. `DB2SimpleDataSource` is one of the IBM Data Server Driver for JDBC and SQLJ implementations of the `DataSource` interface. See "Creating and deploying DataSource objects" for information on the `DataSource` implementations of Db2.
3	The `setDatabaseName`, `setDescription`, `setUser`, and `setPassword` methods assign attributes to the DB2SimpleDataSource object. See "Properties for the IBM Data Server Driver for JDBC and SQLJ" for information about the attributes that you can set for a `DB2SimpleDataSource` object under the IBM Data Server Driver for JDBC and SQLJ.

Note	Description
4	Establishes a connection to the data source that `DB2SimpleDataSource` object dbds represents.

Related tasks

"Connecting to a data source using SQLJ" on page 121
In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

How to determine which type of IBM Data Server Driver for JDBC and SQLJ connectivity to use

The IBM Data Server Driver for JDBC and SQLJ supports two types of connectivity: type 2 connectivity and type 4 connectivity.

For the `DriverManager` interface, you specify the type of connectivity through the URL in the `DriverManager.getConnection` method. For the `DataSource` interface, you specify the type of connectivity through the `driverType` property.

The following table summarizes the differences between type 2 connectivity and type 4 connectivity:

Table 5. Comparison of IBM Data Server Driver for JDBC and SQLJ type 2 connectivity and IBM Data Server Driver for JDBC and SQLJ type 4 connectivity

Function	IBM Data Server Driver for JDBC and SQLJ type 2 connectivity support	IBM Data Server Driver for JDBC and SQLJ type 4 connectivity support
Performance	Better for accessing a local data server	Better for accessing a remote data server
Installation	Requires installation of native libraries in addition to Java classes	Requires installation of Java classes only
Stored procedures	Can be used to call or execute stored procedures	Can be used only to call stored procedures
Distributed transaction processing (XA)	Not supported	Supported
J2EE 1.4 compliance	Compliant	Compliant
CICS environment	Supported	Not supported
IMS environment	Supported	Not supported

The following points can help you determine which type of connectivity to use.

Use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity under these circumstances:

- Your JDBC or SQLJ application runs locally most of the time.

  Local applications have better performance with type 2 connectivity.
- You are *running* a Java stored procedure.

  A stored procedure environment consists of two parts: a client program, from which you call a stored procedure, and a server program, which is the stored procedure. You can call a stored procedure in a JDBC or SQLJ program that uses type 2 or type 4 connectivity, but you must run a Java stored procedure using type 2 connectivity.
- Your application runs in the CICS environment or IMS environment.

Use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity under these circumstances:

- Your JDBC or SQLJ application runs remotely most of the time.

  Remote applications have better performance with type 4 connectivity.
- You are using IBM Data Server Driver for JDBC and SQLJ connection concentrator and sysplex workload balancing support.

JDBC connection objects

When you connect to a data source by either connection method, you create a `Connection` object, which represents the connection to the data source.

You use this `Connection` object to do the following things:

- Create `Statement`, `PreparedStatement`, and `CallableStatement` objects for executing SQL statements. These are discussed in "Executing SQL statements in JDBC applications".
- Gather information about the data source to which you are connected. This process is discussed in "Learning about a data source using DatabaseMetaData methods".
- Commit or roll back transactions. You can commit transactions manually or automatically. These operations are discussed in "Commit or roll back a JDBC transaction".
- Close the connection to the data source. This operation is discussed in "Disconnecting from data sources in JDBC applications".

Related concepts

“JDBC interfaces for executing SQL” on page 30
You execute SQL statements in a traditional SQL program to update data in tables, retrieve data from the tables, or call stored procedures. To perform the same functions in a JDBC program, you invoke methods.

Related tasks

“Learning about a data source using DatabaseMetaData methods” on page 25
The `DatabaseMetaData` interface contains methods that retrieve information about a data source. These methods are useful when you write generic applications that can access various data sources.

“Committing or rolling back JDBC transactions” on page 107
In JDBC, to commit or roll back transactions explicitly, use the `commit` or `rollback` methods.

“Disconnecting from data sources in JDBC applications” on page 117
When you have finished with a connection to a data source, it is *essential* that you close the connection to the data source. Doing this releases the `Connection` object's database and JDBC resources immediately.

Creating and deploying DataSource objects

JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

About this task

Using the `DataSource` interface involves two parts:

- Creating and deploying `DataSource` objects. This is usually done by a system administrator, using a tool such as WebSphere Application Server.
- Using the `DataSource` objects to create a connection. This is done in the application program.

This topic contains information that you need if you create and deploy the `DataSource` objects yourself.

The IBM Data Server Driver for JDBC and SQLJ provides the following `DataSource` implementations:

- `com.ibm.db2.jcc.DB2SimpleDataSource`, which does not support connection pooling. You can use this implementation with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

- `com.ibm.db2.jcc.DB2ConnectionPoolDataSource`, which supports connection pooling. You can use this implementation with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.
- `com.ibm.db2.jcc.DB2XADataSource`, which supports connection pooling and distributed transactions. The connection pooling is provided by WebSphere Application Server or another application server. You can use this implementation only with IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

Procedure

To create and deploy a `DataSource` object, you need to perform these tasks:

1. Create an instance of the appropriate `DataSource` implementation.
2. Set the properties of the `DataSource` object.
3. Register the object with the Java Naming and Directory Interface (JNDI) naming service.

Example

The following example shows how to perform these tasks.

```
import java.sql.*;        // JDBC base
import javax.naming.*;    // JNDI Naming Services
import javax.sql.*;       // Additional methods for JDBC
import com.ibm.db2.jcc.*; // IBM Data Server Driver for
                          // JDBC and SQLJ
                          // implementation of JDBC
                          // standard extension APIs

DB2SimpleDataSource dbds = new com.ibm.db2.jcc.DB2SimpleDataSource();  1

dbds.setDatabaseName("db2loc1");                                       2
dbds.setDescription("Our Sample Database");
dbds.setUser("john");
dbds.setPassword("mypw");
…
Context ctx=new InitialContext();                                      3
Ctx.bind("jdbc/sampledb",dbds);                                        4
```

Figure 6. Example of creating and deploying a DataSource object

Note	Description
1	Creates an instance of the DB2SimpleDataSource class.
2	This statement and the next three statements set values for properties of this `DB2SimpleDataSource` object.
3	Creates a context for use by JNDI.
4	Associates `DBSimple2DataSource` object dbds with the logical name jdbc/sampledb. An application that uses this object can refer to it by the name jdbc/sampledb.

Related tasks

"Connecting to a data source using the DataSource interface" on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223

IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

Java packages for JDBC support

Before you can invoke JDBC methods, you need to be able to access all or parts of various Java packages that contain those methods.

You can do that either by importing the packages or specific classes, or by using the fully-qualified class names. You might need the following packages or classes for your JDBC program:

java.sql
Contains the core JDBC API.

javax.naming
Contains classes and interfaces for Java Naming and Directory Interface (JNDI), which is often used for implementing a `DataSource`.

javax.sql
Contains methods for producing server-side applications using Java

com.ibm.db2.jcc
Contains the implementation of JDBC for the IBM Data Server Driver for JDBC and SQLJ.

Related concepts

"Example of a simple JDBC application" on page 9
A simple JDBC application demonstrates the basic elements that JDBC applications need to include.

Learning about a data source using DatabaseMetaData methods

The `DatabaseMetaData` interface contains methods that retrieve information about a data source. These methods are useful when you write generic applications that can access various data sources.

About this task

In generic applications that can access various data sources, you need to test whether a data source can handle various database operations before you execute them. For example, you need to determine whether the driver at a data source is at the JDBC 4.0 level before you invoke JDBC 4.0 methods against that driver.

`DatabaseMetaData` methods provide the following types of information:

- Features that the data source supports, such as the ANSI SQL level
- Specific information about the JDBC driver, such as the driver level
- Limits, such as the maximum number of columns that an index can have
- Whether the data source supports data definition statements (CREATE, ALTER, DROP, GRANT, REVOKE)
- Lists of objects at the data source, such as tables, indexes, or procedures
- Whether the data source supports various JDBC functions, such as batch updates or scrollable `ResultSets`
- A list of scalar functions that the driver supports

Procedure

To invoke `DatabaseMetaData` methods, you need to perform these basic steps:

1. Create a `DatabaseMetaData` object by invoking the `getMetaData` method on the connection.
2. Invoke `DatabaseMetaData` methods to get information about the data source.
3. If the method returns a `ResultSet`:
   a) In a loop, position the cursor using the `next` method, and retrieve data from each column of the current row of the `ResultSet` object using `getXXX` methods.

b) Invoke the `close` method to close the `ResultSet` object.

Examples

Example: The following code demonstrates how to use `DatabaseMetaData` methods to determine the driver version, to get a list of the stored procedures that are available at the data source, and to get a list of datetime functions that the driver supports. The numbers to the right of selected statements correspond to the previously-described steps.

Figure 7. Using DatabaseMetaData methods to get information about a data source

```
Connection con;
DatabaseMetaData dbmtadta;
ResultSet rs;
int mtadtaint;
String procSchema;
String procName;
String dtfnList;
…
dbmtadta = con.getMetaData();     // Create the DatabaseMetaData object 1
mtadtaint = dbmtadta.getDriverVersion();                                 2
                                  // Check the driver version
System.out.println("Driver version: " + mtadtaint);
rs = dbmtadta.getProcedures(null, null, "%");
                                  // Get information for all procedures
while (rs.next()) {               // Position the cursor                 3a
 procSchema = rs.getString("PROCEDURE_SCHEM");
                                  // Get procedure schema
 procName = rs.getString("PROCEDURE_NAME");
                                  // Get procedure name
 System.out.println(procSchema + "." + procName);
                                  // Print the qualified procedure name
}
dtfnList = dbmtadta.getTimeDateFunctions();
                                  // Get list of supported datetime functions
System.out.println("Supported datetime functions:");
System.out.println(dtfnList);     // Print the list of datetime functions
rs.close();                       // Close the ResultSet                 3b
```

Related reference

“Driver support for JDBC APIs” on page 318
The JDBC drivers that are supported by Db2 and IBM Informix database systems have different levels of support for JDBC methods.

DatabaseMetaData methods for identifying the type of data server

Use the `DatabaseMetaData.getDatabaseProductVersion` method to identify the data server to which an application is connected. Use the `DatabaseMetaData.getDatabaseProductName` method to obtain additional information about the data server.

Important: `DatabaseMetaData.getDatabaseProductVersion` is the preferred method for determining the data server and version because the returned value is in the standard product identifier (PRDID) format.

The format for data servers other than Db2 on Linux, UNIX, and Windows systems is:

```
pppvvrrm
```

The format for Db2 on Linux, UNIX, and Windows systemsdata servers is:

```
pppvvrrmf
```

The parts of the product identifier are

ppp
The 3-byte product code:

ARI
Db2 Server for VM and VSE

DSN
Db2 for z/OS

QSQ
Db2 for IBM i

SQL
Db2 on Linux, UNIX, and Windows systems

vv
The 2-byte version identifier.

rr
The 2-byte release identifier.

m
The 1-byte modification identifier.

f
The 1-byte fix pack identifier. The fix pack identifier is included only for Db2 on Linux, UNIX, and Windows systems data servers.

The following table shows examples of values that are returned by `DatabaseMetaData.getDatabaseProductVersion`.

Table 6. Examples of values returned by `DatabaseMetaData.getDatabaseProductVersion`

Returned value	Database product version
DSN11015	Db2 for z/OS Version 11 in new-function mode
SQL11010	Db2 on Linux, UNIX, and Windows systems Version 11.1 GA
SQL110122	Db2 on Linux, UNIX, and Windows systems Version 11.1 mod pack 2 fix pack 2
IFX11100	IBM Informix Version 11.10

`DatabaseMetaData.getDatabaseProductName` is a method for obtaining additional information about the data server and its operating system. `DatabaseMetaData.getDatabaseProductName` returns a free-form string.

Important: Do not use `DatabaseMetaData.getDatabaseProductName` as the only method for determining the data server type. The contents of the returned string might change between data server versions and between driver versions.

The following table shows examples of values that are returned by `DatabaseMetaData.getDatabaseProductName`.

Table 7. Examples of values returned by `DatabaseMetaData.getDatabaseProductName`

Returned value	Database product
Db2	Db2 for z/OS
Db2 for z/OS VUE	Db2 for z/OS Value Unit Edition
Db2/LINUXX8664	Db2 on Linux on x86
IBM Informix/UNIX64	IBM Informix on UNIX

Using DatabaseMetaData extensions to identify the Db2 Connect version and the IBM Data Server Driver for JDBC and SQLJ version

The DB2DatabaseMetaData.getDriverDB2ConnectLevel method identifies the version of Db2 Connect and the IBM Data Server Driver for JDBC and SQLJ version that an application is using for a connection to a data server.

About this task

Use the DB2DatabaseMetaData.getDriverDB2ConnectLevel method to identify the Db2 Connect version and the IBM Data Server Driver for JDBC and SQLJ version that an application is using for a connection to a data server.

Procedure

To invoke DB2DatabaseMetaData.getDriverDB2ConnectLevel method, you need to perform these basic steps:

1. Create a DatabaseMetaData object by invoking the getMetaData method on the connection, and casting the DatabaseMetaData object to a DB2DatabaseMetaData object.
2. Invoke the DB2DatabaseMetaData.getDriverDB2ConnectLevel method to get information about the Db2 Connect and IBM Data Server Driver for JDBC and SQLJ versions.

Example

The following code demonstrates how to use the DB2DatabaseMetaData.getDriverDB2ConnectLevel method to determine the Db2 Connect and IBM Data Server Driver for JDBC and SQLJ versions.

```
Connection con;
com.ibm.db2.jcc.DB2DatabaseMetaData dbmd;
String versionDetails;

dbmd = (DB2DatabaseMetaData) con.getMetaData();      // Create the DB2DatabaseMetaData object
versionDetails = dbmd.getDriverDB2ConnectLevel();    // Check the version of DB2Connect while
                                                     // requesting IBM data server driver for
                                                     // JDBC and SQLJ version driver version
System.out.println("DB2Connect version: " + versionDetails);
```

Variables in JDBC applications

As in any other Java application, when you write JDBC applications, you declare variables. In Java applications, those variables are known as Java identifiers.

Some of those identifiers have the same function as host variables in other languages: they hold data that you pass to or retrieve from database tables. Identifier empNo in the following code holds data that you retrieve from the EMPNO table column, which has the CHAR data type.

```
String empNo;
// Execute a query and generate a ResultSet instance
rs = stmt.executeQuery("SELECT EMPNO FROM EMPLOYEE");
while (rs.next()) {
 String empNo = rs.getString(1);
 System.out.println("Employee number = " + empNo);
}
```

Your choice of Java data types can affect performance because the data server picks better access paths when the data types of your Java variables map closely to the data server data types.

Related concepts

"Example of a simple JDBC application" on page 9

A simple JDBC application demonstrates the basic elements that JDBC applications need to include.

Related reference

"Data types that map to database data types in Java applications" on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

Comments in a JDBC application

To document your JDBC program, you need to include comments. You can use Java comments outside of JDBC methods and Java or SQL comments in SQL statement strings.

You can include Java comments outside JDBC methods, wherever the Java language permits them. Within an SQL statement string in a JDBC method call, you can use comments in the following places:

- For connections to Db2 on Linux, UNIX, and Windows systems data servers or Informix data servers, comments can be:
  - Anywhere in the SQL statement string, and enclosed in /* and */ pairs. /* and */ pairs can be nested.
  - At the end of the SQL statement string, and preceded by two hyphens (--).
- For connections to Informix data servers only, comments can be enclosed in left curly bracket ({) and right curly bracket (}) pairs.

  Restriction: A comment that is enclosed in a { and } pair is not valid if either of the following conditions is true:

  - The SQL statement string is not a stored procedure call, the SQL statement string is preceded and followed by comments that are enclosed in { and } pairs, and the comment at the beginning of the SQL statement string begins with the word `call`.
  - The SQL statement string is a stored procedure call, and the comment {call} is at the beginning of the escape syntax for the stored procedure call.
  - The comment contains any of the following characters:
    - Single quotation mark (')
    - Double quotation mark (")
    - Left curly bracket ({)
    - Right curly bracket (})
    - /*
  - The comment can be interpreted as SQL escape syntax. Comments that begin with the following characters can be interpreted as SQL escape syntax:
    - d followed by a space
    - t followed by a space
    - ts followed by a space
    - escape followed by a space
    - oj followed by a space
    - fn followed by a space

  For example, the following SQL statement strings are not valid:

```
"{call comment at beginning} select * from systables {ending comment}"
"{{call} call mysp(?, ?)}"
```

JDBC interfaces for executing SQL

You execute SQL statements in a traditional SQL program to update data in tables, retrieve data from the tables, or call stored procedures. To perform the same functions in a JDBC program, you invoke methods.

Those methods are defined in the following interfaces:

- The `Statement` interface supports all SQL statement execution. The following interfaces inherit methods from the `Statement` interface:
  - The `PreparedStatement` interface supports any SQL statement containing input parameter markers. Parameter markers represent input variables. The `PreparedStatement` interface can also be used for SQL statements with no parameter markers.

    With the IBM Data Server Driver for JDBC and SQLJ, the `PreparedStatement` interface can be used to call stored procedures that have input parameters and no output parameters, and that return no result sets. However, the preferred interface is `CallableStatement`.
  - The `CallableStatement` interface supports the invocation of a stored procedure.

    The `CallableStatement` interface can be used to call stored procedures with input parameters, output parameters, or input and output parameters, or no parameters. With the IBM Data Server Driver for JDBC and SQLJ, you can also use the `Statement` interface to call stored procedures, but those stored procedures must have no parameters.
- The `ResultSet` interface provides access to the results that a query generates. The `ResultSet` interface has the same purpose as the cursor that is used in SQL applications in other languages.

Related tasks

"Creating and modifying database objects using the Statement.executeUpdate method" on page 30
The `Statement.executeUpdate` is one of the JDBC methods that you can use to update tables and call stored procedures.

"Retrieving data from tables using the Statement.executeQuery method" on page 38
To retrieve data from a table using a SELECT statement with no parameter markers, you can use the `Statement.executeQuery` method.

"Updating data in tables using the PreparedStatement.executeUpdate method" on page 31
The `Statement.executeUpdate` method works if you update data server tables with constant values. However, updates often need to involve passing values in variables to the tables. To do that, you use the `PreparedStatement.executeUpdate` method.

"Retrieving data from tables using the PreparedStatement.executeQuery method" on page 39
To retrieve data from a table using a SELECT statement with parameter markers, you use the `PreparedStatement.executeQuery` method.

Creating and modifying database objects using the Statement.executeUpdate method

The `Statement.executeUpdate` is one of the JDBC methods that you can use to update tables and call stored procedures.

About this task

You can use the `Statement.executeUpdate` method to do the following things:

- Execute data definition statements, such as CREATE, ALTER, DROP, GRANT, REVOKE
- Execute INSERT, UPDATE, DELETE, and MERGE statements that do not contain parameter markers.
- With the IBM Data Server Driver for JDBC and SQLJ, execute the CALL statement to call stored procedures that have no parameters and that return no result sets.

Procedure

To execute these SQL statements, you need to perform these steps:

1. Invoke the `Connection.createStatement` method to create a `Statement` object.
2. Invoke the `Statement.executeUpdate` method to perform the SQL operation.
3. Invoke the `Statement.close` method to close the `Statement` object.

Example

Suppose that you want to execute this SQL statement:

```
UPDATE EMPLOYEE SET PHONENO='4657' WHERE EMPNO='000010'
```

The following code creates `Statement` object `stmt`, executes the UPDATE statement, and returns the number of rows that were updated in numUpd. The numbers to the right of selected statements correspond to the previously-described steps.

```
Connection con;
Statement stmt;
int numUpd;
…
stmt = con.createStatement();                // Create a Statement object  1
numUpd = stmt.executeUpdate(
  "UPDATE EMPLOYEE SET PHONENO='4657' WHERE EMPNO='000010'");             2
                                             // Perform the update
stmt.close();                                // Close Statement object     3
```

Figure 8. Using Statement.executeUpdate

Updating data in tables using the PreparedStatement.executeUpdate method

The `Statement.executeUpdate` method works if you update data server tables with constant values. However, updates often need to involve passing values in variables to the tables. To do that, you use the `PreparedStatement.executeUpdate` method.

About this task

With the IBM Data Server Driver for JDBC and SQLJ, you can also use `PreparedStatement.executeUpdate` to call stored procedures that have input parameters and no output parameters, and that return no result sets.

Db2 for z/OS does not support dynamic execution of the CALL statement. For calls to stored procedures that are on Db2 for z/OS data sources, the parameters can be parameter markers or literals, but not expressions. The following types of literals are supported:

- Integer
- Double
- Decimal
- Character
- Hexadecimal
- Graphic

For calls to stored procedures that are on IBM Informix data sources, the `PreparedStatement` object can be a CALL statement or an EXECUTE PROCEDURE statement.

When you execute an SQL statement many times, you can get better performance by creating the SQL statement as a `PreparedStatement`.

For example, the following UPDATE statement lets you update the employee table for only one phone number and one employee number:

```
UPDATE EMPLOYEE SET PHONENO='4657' WHERE EMPNO='000010'
```

Suppose that you want to generalize the operation to update the employee table for any set of phone numbers and employee numbers. You need to replace the constant phone number and employee number with variables:

```
UPDATE EMPLOYEE SET PHONENO=? WHERE EMPNO=?
```

Variables of this form are called parameter markers.

Procedure

To execute an SQL statement with parameter markers, you need to perform these steps:

1. Invoke the `Connection.prepareStatement` method to create a `PreparedStatement` object.
2. Invoke the `PreparedStatement.setXXX` methods to pass values to the input variables.

   This step assumes that you use standard parameter markers. Alternatively, if you use named parameter markers, you useIBM Data Server Driver for JDBC and SQLJ-only methods to pass values to the input parameters.
3. Invoke the `PreparedStatement.executeUpdate` method to update the table with the variable values.
4. Invoke the `PreparedStatement.close` method to close the `PreparedStatement` object when you have finished using that object.

Example

The following code performs the previous steps to update the phone number to '4657' for the employee with employee number '000010'. The numbers to the right of selected statements correspond to the previously-described steps.

```
Connection con;
PreparedStatement pstmt;
int numUpd;
…
pstmt = con.prepareStatement(
  "UPDATE EMPLOYEE SET PHONENO=? WHERE EMPNO=?");
                                // Create a PreparedStatement object       1
pstmt.setString(1,"4657");      // Assign first value to first parameter   2
pstmt.setString(2,"000010");    // Assign first value to second parameter
numUpd = pstmt.executeUpdate(); // Perform first update                    3
pstmt.setString(1,"4658");      // Assign second value to first parameter
pstmt.setString(2,"000020");    // Assign second value to second parameter
numUpd = pstmt.executeUpdate(); // Perform second update
pstmt.close();                  // Close the PreparedStatement object     4
```

Figure 9. Using PreparedStatement.executeUpdate for an SQL statement with parameter markers

You can also use the `PreparedStatement.executeUpdate` method for statements that have no parameter markers. The steps for executing a `PreparedStatement` object with no parameter markers are similar to executing a `PreparedStatement` object with parameter markers, except you skip step “2” on page 32. The following example demonstrates these steps.

```
Connection con;
PreparedStatement pstmt;
int numUpd;
…
pstmt = con.prepareStatement(
  "UPDATE EMPLOYEE SET PHONENO='4657' WHERE EMPNO='000010'");
                                // Create a PreparedStatement object  1
numUpd = pstmt.executeUpdate(); // Perform the update                 3
pstmt.close();                  // Close the PreparedStatement object 4
```

Figure 10. Using PreparedStatement.executeUpdate for an SQL statement without parameter markers

Related tasks

"Using named parameter markers with PreparedStatement objects" on page 77
You can use named parameter markers instead of standard parameter markers in `PreparedStatement` objects to assign values to the parameter markers.

JDBC executeUpdate methods against a Db2 for z/OS server

The JDBC standard states that the executeUpdate method returns a row count or 0. However, if the executeUpdate method is executed against a Db2 for z/OS server, it can return a value of -1.

For `executeUpdate` statements against a Db2 for z/OS server, the value that is returned depends on the type of SQL statement that is being executed:

- For an SQL statement that can have an update count, such as an INSERT, UPDATE, DELETE, or MERGE statement, the returned value is the number of affected rows. It can be:
  - A positive number, if a positive number of rows are affected by the operation, and the operation is not a mass delete on a segmented table space.
  - 0, if no rows are affected by the operation.
  - -1, if the operation is a mass delete on a segmented table space.
- For an SQL CALL statement, a value of -1 is returned, because the data source cannot determine the number of affected rows. Calls to `getUpdateCount` or `getMoreResults` for a CALL statement also return -1.
- For any other SQL statement, a value of -1 is returned.

Related tasks

"Creating and modifying database objects using the Statement.executeUpdate method" on page 30
The `Statement.executeUpdate` is one of the JDBC methods that you can use to update tables and call stored procedures.

Making batch updates in JDBC applications

With batch updates, instead of updating rows of a table one at a time, you can direct JDBC to execute a group of updates at the same time. Statements that can be included in the same batch of updates are known as *batchable* statements.

About this task

If a statement has input parameters or host expressions, you can include that statement only in a batch that has other instances of the same statement. This type of batch is known as a *homogeneous batch*. If a statement has no input parameters, you can include that statement in a batch only if the other statements in the batch have no input parameters or host expressions. This type of batch is known as a *heterogeneous batch*. Two statements that can be included in the same batch are known as *batch compatible*.

Use the following `Statement` methods for creating, executing, and removing a batch of SQL updates:

- `addBatch`
- `executeBatch`
- `clearBatch`

Use the following `PreparedStatement` and `CallableStatement` method for creating a batch of parameters so that a single statement can be executed multiple times in a batch, with a different set of parameters for each execution.

- `addBatch`

Restrictions on executing statements in a batch:

- If you try to execute a SELECT statement in a batch, a `BatchUpdateException` is thrown.

- A `CallableStatement` object that you execute in a batch can contain output parameters. However, you cannot retrieve the values of the output parameters. If you try to do so, a `BatchUpdateException` is thrown.
- You cannot retrieve `ResultSet` objects from a `CallableStatement` object that you execute in a batch. A `BatchUpdateException` is not thrown, but the `getResultSet` method invocation returns a null value.

Procedure

To make batch updates, follow one of the following sets of steps.

- To make batch updates using several statements with no input parameters, follow these basic steps:
  1. For each SQL statement that you want to execute in the batch, invoke the `addBatch` method.
  2. Invoke the `executeBatch` method to execute the batch of statements.
  3. Check for errors. If no errors occurred:
     a. Get the number of rows that were affect by each SQL statement from the array that the `executeBatch` invocation returns. This number does not include rows that were affected by triggers or by referential integrity enforcement.
     b. If `AutoCommit` is disabled for the `Connection` object, invoke the `commit` method to commit the changes.

        If `AutoCommit` is enabled for the `Connection` object, the IBM Data Server Driver for JDBC and SQLJ adds a `commit` method at the end of the batch.
- To make batch updates using a single statement with several sets of input parameters, follow these basic steps:
  1. If the batched statement is a searched UPDATE, searched DELETE, or MERGE statement, set the autocommit mode for the connection to `false`.
  2. Invoke the `prepareStatement` method to create a `PreparedStatement` object.
  3. For each set of input parameter values:
     a. Execute `setXXX` methods to assign values to the input parameters.
     b. Invoke the `addBatch` method to add the set of input parameters to the batch.
  4. Invoke the `executeBatch` method to execute the statements with all sets of parameters.
  5. If no errors occurred:
     a. Get the number of rows that were updated by each execution of the SQL statement from the array that the `executeBatch` invocation returns. The number of affected rows does not include rows that were affected by triggers or by referential integrity enforcement.

        If the following conditions are true, the IBM Data Server Driver for JDBC and SQLJ returns `Statement.SUCCESS_NO_INFO` (-2), instead of the number of rows that were affected by each SQL statement:

        – The application is connected to a subsystem that is in Db2 for z/OS Version 8 new-function mode, or later.
        – The application is using Version 3.1 or later of the IBM Data Server Driver for JDBC and SQLJ.
        – The IBM Data Server Driver for JDBC and SQLJ uses multi-row INSERT operations to execute batch updates.

        This occurs because with multi-row INSERT, the database server executes the entire batch as a single operation, so it does not return results for individual SQL statements.
     b. If `AutoCommit` is disabled for the `Connection` object, invoke the `commit` method to commit the changes.

        If `AutoCommit` is enabled for the `Connection` object, the IBM Data Server Driver for JDBC and SQLJ adds a `commit` method at the end of the batch.

c. If the `PreparedStatement` object returns automatically generated keys, call `DB2PreparedStatement.getDBGeneratedKeys` to retrieve an array of `ResultSet` objects that contains the automatically generated keys.

   Check the length of the returned array. If the length of the returned array is 0, an error occurred during retrieval of the automatically generated keys.

6. If errors occurred, process the `BatchUpdateException`.

Example

In the following code fragment, two sets of parameters are batched. An UPDATE statement that takes two input parameters is then executed twice, once with each set of parameters. The numbers to the right of selected statements correspond to the previously-described steps.

```
try {
…
  PreparedStatement preps = conn.prepareStatement(
    "UPDATE DEPT SET MGRNO=? WHERE DEPTNO=?");          2
  ps.setString(1,mgrnum1);                              3a
  ps.setString(2,deptnum1);
  ps.addBatch();                                        3b

  ps.setString(1,mgrnum2);
  ps.setString(2,deptnum2);
  ps.addBatch();
  int [] numUpdates=ps.executeBatch();                  4
  for (int i=0; i < numUpdates.length; i++) {           5a
    if (numUpdates[i] == SUCCESS_NO_INFO)
      System.out.println("Execution " + i +
        ": unknown number of rows updated");
    else
      System.out.println("Execution " + i +
        "successful: " numUpdates[i] + " rows updated");
  }
  conn.commit();                                        5b
} catch(BatchUpdateException b) {                       6
  // process BatchUpdateException
}
```

In the following code fragment, a batched INSERT statement returns automatically generated keys.

```
import java.sql.*;
import com.ibm.db2.jcc.*;
…
Connection conn;
…
try {
…
  PreparedStatement ps = conn.prepareStatement(         2
    "INSERT INTO DEPT (DEPTNO, DEPTNAME, ADMRDEPT) " +
    "VALUES (?,?,?)",
    Statement.RETURN_GENERATED_KEYS);
  ps.setString(1,"X01");                                3a
  ps.setString(2,"Finance");
  ps.setString(3,"A00");
  ps.addBatch();                                        3b
  ps.setString(1,"Y01");
  ps.setString(2,"Accounting");
  ps.setString(3,"A00");
  ps.addBatch();

  int [] numUpdates=preps.executeBatch();               4

  for (int i=0; i < numUpdates.length; i++) {           5a
    if (numUpdates[i] == SUCCESS_NO_INFO)
      System.out.println("Execution " + i +
        ": unknown number of rows updated");
    else
      System.out.println("Execution " + i +
        "successful: " numUpdates[i] + " rows updated");
  }
  conn.commit();                                        5b
  ResultSet[] resultList =
    ((DB2PreparedStatement)ps).getDBGeneratedKeys();    5c
  if (resultList.length != 0) {
```

```
    for (i = 0; i < resultList.length; i++) {
        while (resultList[i].next()) {
          java.math.BigDecimal idColVar = rs.getBigDecimal(1);
                              // Get automatically generated key
                              // value
          System.out.println("Automatically generated key value = "
            + idColVar);
        }
    }
  }
  else {
    System.out.println("Error retrieving automatically generated keys");
  }
} catch(BatchUpdateException b) {                          6
  // process BatchUpdateException
}
```

In the following code fragment, a batched UPDATE statement returns automatically generated keys. The code names the DEPTNO column as an automatically generated key, updates two rows in the DEPT table in a batch, and retrieves the values of DEPTNO for the updated rows. The numbers to the right of selected statements correspond to the previously described steps.

```
import java.sql.*;
import com.ibm.db2.jcc.*;
…
Connection conn;
…
String[] agkNames = {"DEPTNO"};
try {
…
  conn.setAutoCommit(false);                               1
  PreparedStatement ps = conn.prepareStatement(            2
    "UPDATE DEPT SET  DEPTNAME=? " +
    "WHERE DEPTNO=?",agkNames);
  ps.setString(1,"X01");                                   3a
  ps.setString(2,"Planning");
  ps.addBatch();                                           3b
  ps.setString(1,"Y01");
  ps.setString(2,"Bookkeeping");
  ps.addBatch();

  int [] numUpdates=ps.executeBatch();                     4

  for (int i=0; i < numUpdates.length; i++) {              5a
    if (numUpdates[i] == SUCCESS_NO_INFO)
      System.out.println("Execution " + i +
        ": unknown number of rows updated");
    else
      System.out.println("Execution " + i +
        "successful: " numUpdates[i] + " rows updated");
  }
  conn.commit();                                           5b
  ResultSet[] resultList =
    ((DB2PreparedStatement)ps).getDBGeneratedKeys();       5c
  if (resultList.length != 0) {
    for (i = 0; i < resultList.length; i++) {
        while (resultList[i].next()) {
          String deptNoKey = rs.getString(1);
                              // Get automatically generated key
                              // value
          System.out.println("Automatically generated key value = "
            + deptNoKey);
        }
    }
  }
  else {
    System.out.println("Error retrieving automatically generated keys");
  }
}
catch(BatchUpdateException b) {                            6
  // process BatchUpdateException
}
```

Related tasks

“Making batch updates in SQLJ applications” on page 138

The IBM Data Server Driver for JDBC and SQLJ supports batch updates in SQLJ. With batch updates, instead of updating rows of a table one at a time, you can direct SQLJ to execute a group of updates at the same time.

"Retrieving information from a BatchUpdateException" on page 115
When an error occurs during execution of a statement in a batch, processing continues. However, `executeBatch` throws a `BatchUpdateException`.

"Making batch queries in JDBC applications" on page 40
The IBM Data Server Driver for JDBC and SQLJ provides a IBM Data Server Driver for JDBC and SQLJ-only `DB2PreparedStatement` interface that lets you perform batch queries on a homogeneous batch.

"Committing or rolling back JDBC transactions" on page 107
In JDBC, to commit or roll back transactions explicitly, use the `commit` or `rollback` methods.

Learning about parameters in a PreparedStatement using ParameterMetaData methods

The IBM Data Server Driver for JDBC and SQLJ includes support for the `ParameterMetaData` interface. The `ParameterMetaData` interface contains methods that retrieve information about the parameter markers in a `PreparedStatement` object.

About this task

`ParameterMetaData` methods provide the following types of information:

- The data types of parameters, including the precision and scale of decimal parameters.
- The parameters' database-specific type names. For parameters that correspond to table columns that are defined with distinct types, these names are the distinct type names.
- Whether parameters are nullable.
- Whether parameters are input or output parameters.
- Whether the values of a numeric parameter can be signed.
- The fully-qualified Java class name that `PreparedStatement.setObject` uses when it sets a parameter value.

Procedure

To invoke `ParameterMetaData` methods, you need to perform these basic steps:

1. Invoke the `Connection.prepareStatement` method to create a `PreparedStatement` object.
2. Invoke the `PreparedStatement.getParameterMetaData` method to retrieve a `ParameterMetaData` object.
3. Invoke `ParameterMetaData.getParameterCount` to determine the number of parameters in the `PreparedStatement`.
4. Invoke `ParameterMetaData` methods on individual parameters.

Example

The following code demonstrates how to use `ParameterMetaData` methods to determine the number and data types of parameters in an SQL UPDATE statement. The numbers to the right of selected statements correspond to the previously-described steps.

```
Connection con;
ParameterMetaData pmtadta;
int mtadtacnt;
String sqlType;
…
pstmt = con.prepareStatement(
  "UPDATE EMPLOYEE SET PHONENO=? WHERE EMPNO=?");
                                  // Create a PreparedStatement object  1
pmtadta = pstmt.getParameterMetaData();                                 2
                                  // Create a ParameterMetaData object
mtadtacnt = pmtadta.getParameterCount();                                3
                                  // Determine the number of parameters
System.out.println("Number of statement parameters: " + mtadtacnt);
for (int i = 1; i <= mtadtacnt; i++) {
  sqlType = pmtadta.getParameterTypeName(i);                            4
                                  // Get SQL type for each parameter
 System.out.println("SQL type of parameter " + i " is " + sqlType);
}
…
pstmt.close();                      // Close the PreparedStatement
```

Figure 11. Using ParameterMetaData methods to get information about a PreparedStatement

Related reference

“Driver support for JDBC APIs” on page 318
The JDBC drivers that are supported by Db2 and IBM Informix database systems have different levels of support for JDBC methods.

Data retrieval in JDBC applications

In JDBC applications, you retrieve data using `ResultSet` objects. A `ResultSet` represents the result set of a query.

Retrieving data from tables using the Statement.executeQuery method

To retrieve data from a table using a SELECT statement with no parameter markers, you can use the `Statement.executeQuery` method.

About this task

This method returns a result table in a `ResultSet` object. After you obtain the result table, you need to use `ResultSet` methods to move through the result table and obtain the individual column values from each row.

With the IBM Data Server Driver for JDBC and SQLJ, you can also use the `Statement.executeQuery` method to retrieve a result set from a stored procedure call, if that stored procedure returns only one result set. If the stored procedure returns multiple result sets, you need to use the `Statement.execute` method.

This topic discusses the simplest kind of `ResultSet`, which is a read-only `ResultSet` in which you can only move forward, one row at a time. The IBM Data Server Driver for JDBC and SQLJ also supports updatable and scrollable `ResultSets`.

Procedure

To retrieve rows from a table using a SELECT statement with no parameter markers, you need to perform these steps:

1. Invoke the `Connection.createStatement` method to create a `Statement` object.
2. Invoke the `Statement.executeQuery` method to obtain the result table from the SELECT statement in a `ResultSet` object.
3. In a loop, position the cursor using the `next` method, and retrieve data from each column of the current row of the `ResultSet` object using `getXXX` methods. XXX represents a data type.
4. Invoke the `ResultSet.close` method to close the `ResultSet` object.

5. Invoke the `Statement.close` method to close the `Statement` object when you have finished using that object.

Example

The following code demonstrates how to retrieve all rows from the employee table. The numbers to the right of selected statements correspond to the previously-described steps.

```
String empNo;
Connection con;
Statement stmt;
ResultSet rs;
…
stmt = con.createStatement();     // Create a Statement object          1
rs = stmt.executeQuery("SELECT EMPNO FROM EMPLOYEE");                   2
                                  // Get the result table from the query
while (rs.next()) {               // Position the cursor               3
 empNo = rs.getString(1);             // Retrieve only the first column value
 System.out.println("Employee number = " + empNo);
                                  // Print the column value
}
rs.close();                       // Close the ResultSet               4
stmt.close();                     // Close the Statement               5
```

Figure 12. Using Statement.executeQuery

Retrieving data from tables using the PreparedStatement.executeQuery method

To retrieve data from a table using a SELECT statement with parameter markers, you use the `PreparedStatement.executeQuery` method.

About this task

This method returns a result table in a `ResultSet` object. After you obtain the result table, you need to use `ResultSet` methods to move through the result table and obtain the individual column values from each row.

With the IBM Data Server Driver for JDBC and SQLJ, you can also use the `PreparedStatement.executeQuery` method to retrieve a result set from a stored procedure call, if that stored procedure returns only one result set and has only input parameters. If the stored procedure returns multiple result sets, you need to use the `PreparedStatement.execute` method.

You can also use the `PreparedStatement.executeQuery` method for statements that have no parameter markers. When you execute a query many times, you can get better performance by creating the SQL statement as a `PreparedStatement`.

Procedure

To retrieve rows from a table using a SELECT statement with parameter markers, you need to perform these steps:

1. Invoke the `Connection.prepareStatement` method to create a `PreparedStatement` object.
2. Invoke `PreparedStatement.setXXX` methods to pass values to the input parameters.
3. Invoke the `PreparedStatement.executeQuery` method to obtain the result table from the SELECT statement in a `ResultSet` object.

   Restriction: For a `PreparedStatement` that contains an IN predicate, the expression that is the argument of the IN predicate cannot have more than 32767 parameters if the target data server is a Db2 on Linux, UNIX, and Windows systems system. Otherwise, the IBM Data Server Driver for JDBC and SQLJ throws an `SQLException` with error code -4499.
4. In a loop, position the cursor using the `ResultSet.next` method, and retrieve data from each column of the current row of the `ResultSet` object using `getXXX` methods.
5. Invoke the `ResultSet.close` method to close the `ResultSet` object.

6. Invoke the `PreparedStatement.close` method to close the `PreparedStatement` object when you have finished using that object.

Example

The following code demonstrates how to retrieve rows from the employee table for a specific employee. The numbers to the right of selected statements correspond to the previously-described steps.

```
String empnum, phonenum;
Connection con;
PreparedStatement pstmt;
ResultSet rs;
…
pstmt = con.prepareStatement(
  "SELECT EMPNO, PHONENO FROM EMPLOYEE WHERE EMPNO=?");
                                  // Create a PreparedStatement object   1
pstmt.setString(1,"000010");      // Assign value to input parameter     2

rs = pstmt.executeQuery();        // Get the result table from the query 3
while (rs.next()) {               // Position the cursor                 4
 empnum = rs.getString(1);        // Retrieve the first column value
 phonenum = rs.getString(2);      // Retrieve the first column value
 System.out.println("Employee number = " + empnum +
   "Phone number = " + phonenum);
                                  // Print the column values
}
rs.close();                       // Close the ResultSet                 5
pstmt.close();                    // Close the PreparedStatement         6
```

Figure 13. Example of using PreparedStatement.executeQuery

Making batch queries in JDBC applications

The IBM Data Server Driver for JDBC and SQLJ provides a IBM Data Server Driver for JDBC and SQLJ-only `DB2PreparedStatement` interface that lets you perform batch queries on a homogeneous batch.

Procedure

To make batch queries using a single statement with several sets of input parameters, follow these basic steps:

1. Invoke the `prepareStatement` method to create a `PreparedStatement` object for the SQL statement with input parameters.
2. For each set of input parameter values:
   a) Execute `PreparedStatement.setXXX` methods to assign values to the input parameters.
   b) Invoke the `PreparedStatement.addBatch` method to add the set of input parameters to the batch.
3. Cast the `PreparedStatement` object to a `DB2PreparedStatement` object, and invoke the `DB2PreparedStatement.executeDB2QueryBatch` method to execute the statement with all sets of parameters.
4. In a loop, retrieve the `ResultSet` objects:
   a) Retrieve each `ResultSet` object.
   b) Retrieve all the rows from each `ResultSet` object.

Example

In the following code fragment, two sets of parameters are batched. A SELECT statement that takes one input parameter is then executed twice, once with each parameter value. The numbers to the right of selected statements correspond to the previously described steps.

```
java.sql.Connection con = java.sql.DriverManager.getConnection(url, properties);
java.sql.Statement s = con.createStatement();
// Clean up from previous executions
try {
  s.executeUpdate ("drop table TestQBatch");
```

```
}
catch (Exception e) {
}

// Create and populate a test table
s.executeUpdate ("create table TestQBatch (col1 int, col2 char(10))");
s.executeUpdate ("insert into TestQBatch values (1, 'test1')");
s.executeUpdate ("insert into TestQBatch values (2, 'test2')");
s.executeUpdate ("insert into TestQBatch values (3, 'test3')");
s.executeUpdate ("insert into TestQBatch values (4, 'test4')");
s.executeUpdate ("insert into TestQBatch values (1, 'test5')");
s.executeUpdate ("insert into TestQBatch values (2, 'test6')");

try {
  PreparedStatement pstmt =                                    1
    con.prepareStatement("Select * from TestQBatch where col1 = ?");
  pstmt.setInt(1,1);                                           2a
  pstmt.addBatch();                                            2b
  // Add some more values to the batch
  pstmt.setInt(1,2);
  pstmt.addBatch();
  pstmt.setInt(1,3);
  pstmt.addBatch();
  pstmt.setInt(1,4);
  pstmt.addBatch();
  ((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).executeDB2QueryBatch();
                                                               3
} catch(BatchUpdateException b) {
  // process BatchUpdateException
}
ResultSet rs;
while(pstmt.getMoreResults()) {                                4
  rs = pstmt.getResultSet();                                   4a
  while (rs.next()) {                                          4b
    System.out.print (rs.getInt (1) + "  ");
    System.out.println (rs.getString (2));
  }
  System.out.println();
  rs.close ();
}
// Clean up
s.close ();
pstmt.close ();
con.close ();
```

Related tasks

“Making batch updates in JDBC applications” on page 33
With batch updates, instead of updating rows of a table one at a time, you can direct JDBC to execute a group of updates at the same time. Statements that can be included in the same batch of updates are known as *batchable* statements.

Learning about a ResultSet using ResultSetMetaData methods

You cannot always know the number of columns and data types of the columns in a table or result set. This is true especially when you are retrieving data from a remote data source.

About this task

When you write programs that retrieve unknown `ResultSets`, you need to use `ResultSetMetaData` methods to determine the characteristics of the `ResultSets` before you can retrieve data from them.

`ResultSetMetaData` methods provide the following types of information:

- The number of columns in a `ResultSet`
- The qualifier for the underlying table of the `ResultSet`
- Information about a column, such as the data type, length, precision, scale, and nullability
- Whether a column is read-only

Procedure

After you invoke the `executeQuery` method to generate a `ResultSet` for a query on a table, follow these basic steps to determine the contents of the `ResultSet`:

1. Invoke the `getMetaData` method on the `ResultSet` object to create a `ResultSetMetaData` object.
2. Invoke the `getColumnCount` method to determine how many columns are in the `ResultSet`.
3. For each column in the `ResultSet`, execute `ResultSetMetaData` methods to determine column characteristics.

   The results of `ResultSetMetaData.getColumnName` call reflects the column name information that is stored in the catalog for that data server.

Example

The following code demonstrates how to determine the data types of all the columns in the employee table. The numbers to the right of selected statements correspond to the previously-described steps.

```
String s;
Connection con;
Statement stmt;
ResultSet rs;
ResultSetMetaData rsmtadta;
int colCount
int mtadtaint;
int i;
String colName;
String colType;
…
stmt = con.createStatement();     // Create a Statement object
rs = stmt.executeQuery("SELECT * FROM EMPLOYEE");
                                  // Get the ResultSet from the query
rsmtadta = rs.getMetaData();      // Create a ResultSetMetaData object  1
colCount = rsmtadta.getColumnCount();                                  2
                                  // Find number of columns in EMP
for (i=1; i<= colCount; i++) {                                         3
 colName = rsmtadta.getColumnName();    // Get column name
 colType = rsmtadta.getColumnTypeName();
                                        // Get column data type
 System.out.println("Column = " + colName +
  " is data type " + colType);
                                        // Print the column value
}
```

Figure 14. Using ResultSetMetaData methods to get information about a ResultSet

Related tasks

“Retrieving data from tables using the Statement.executeQuery method” on page 38
To retrieve data from a table using a SELECT statement with no parameter markers, you can use the `Statement.executeQuery` method.

“Retrieving multiple result sets from a stored procedure in a JDBC application” on page 53
If you call a stored procedure that returns result sets, you need to include code to retrieve the result sets.

“Calling stored procedures in JDBC applications” on page 51
To call stored procedures, you invoke methods in the `CallableStatement` or `PreparedStatement` class.

Characteristics of a JDBC ResultSet under the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ provides support for scrollable, updatable, and holdable cursors.

In addition to moving forward, one row at a time, through a `ResultSet`, you might want to do the following things:

- Move backward or go directly to a specific row

- Update, delete, or insert rows in a `ResultSet`
- Leave the `ResultSet` open after a COMMIT

The following terms describe characteristics of a `ResultSet`:

scrollability
Whether the cursor for the `ResultSet` can move forward only, or forward one or more rows, backward one or more rows, or to a specific row.

If a cursor for a `ResultSet` is scrollable, it also has a sensitivity attribute, which describes whether the cursor is sensitive to changes to the underlying table.

updatability
Whether the cursor can be used to update or delete rows. This characteristic does not apply to a `ResultSet` that is returned from a stored procedure, because a stored procedure `ResultSet` cannot be updated.

holdability
Whether the cursor stays open after a COMMIT.

You set the updatability, scrollability, and holdability characteristics of a `ResultSet` through parameters in the `Connection.prepareStatement` or `Connection.createStatement` methods. The `ResultSet` settings map to attributes of a cursor in the database. The following table lists the JDBC scrollability, updatability, and holdability settings, and the corresponding cursor attributes.

Table 8. JDBC ResultSet characteristics and SQL cursor attributes

JDBC setting	Db2 cursor setting	IBM Informix cursor setting
CONCUR_READ_ONLY	FOR READ ONLY	FOR READ ONLY
CONCUR_UPDATABLE	FOR UPDATE	FOR UPDATE
HOLD_CURSORS_OVER_COMMIT	WITH HOLD	WITH HOLD
TYPE_FORWARD_ONLY	SCROLL not specified	SCROLL not specified
TYPE_SCROLL_INSENSITIVE	INSENSITIVE SCROLL	SCROLL
TYPE_SCROLL_SENSITIVE	SENSITIVE STATIC, SENSITIVE DYNAMIC, or ASENSITIVE, depending on the cursorSensitivity `Connection` and `DataSource` property	Not supported

Important: Like static scrollable cursors in any other language, JDBC static scrollable `ResultSet` objects use declared temporary tables for their internal processing. This means that before you can execute any applications that contain JDBC static scrollable `ResultSet` objects, your database administrator needs to create a temporary database and temporary table spaces for those declared temporary tables.

If a JDBC `ResultSet` is static, the size of the result table and the order of the rows in the result table do not change after the cursor is opened. This means that if you insert rows into the underlying table, the result table for a static `ResultSet` does not change. If you delete a row of a result table, a delete hole occurs. You cannot update or delete a delete hole.

Specifying updatability, scrollability, and holdability for ResultSets in JDBC applications

You use special parameters in the `Connection.prepareStatement` or `Connection.createStatement` methods to specify the updatability, scrollability, and holdability of a `ResultSet`.

Before you begin

If you plan to update `ResultSet` objects, ensure that the enableExtendedDescribe property is not set, or is set to DB2BaseDataSource.YES (2). Updates of `ResultSet` objects do not work correctly unless extended describe capability is enabled.

About this task

By default, `ResultSet` objects are not scrollable and not updatable. The default holdability depends on the data source, and can be determined from the `DatabaseMetaData.getResultSetHoldability` method. These steps change the scrollability, updatability, and holdability attributes for a `ResultSet`.

Procedure

1. If the SELECT statement that defines the `ResultSet` has no input parameters, invoke the `createStatement` method to create a `Statement` object. Otherwise, invoke the `prepareStatement` method to create a `PreparedStatement` object.

   You need to specify forms of the `createStatement` or `prepareStatement` methods that include the *resultSetType*, *resultSetConcurrency*, or *resultSetHoldability* parameters.

   The form of the `createStatement` method that supports scrollability and updatability is:

   ```
   createStatement(int resultSetType, int resultSetConcurrency);
   ```

   The form of the `createStatement` method that supports scrollability, updatability, and holdability is:

   ```
   createStatement(int resultSetType, int resultSetConcurrency,
    int resultSetHoldability);
   ```

   The form of the `prepareStatement` method that supports scrollability and updatability is:

   ```
   prepareStatement(String sql, int resultSetType,
    int resultSetConcurrency);
   ```

   The form of the `prepareStatement` method that supports scrollability, updatability, and holdability is:

   ```
   prepareStatement(String sql, int resultSetType,
    int resultSetConcurrency, int resultSetHoldability);
   ```

   Important: In a `prepareStatement` method invocation in which the first parameter is a CALL statement, you cannot specify the scrollability, updatability, or holdability of result sets that are returned from a stored procedure. Those characteristics are determined by the stored procedure code, when it declares the cursors for the result sets that are returned. If you use the `prepareStatement` method to prepare a CALL statement, and the `prepareStatement` call includes the scrollability, updatability, or holdability parameters, the IBM Data Server Driver for JDBC and SQLJ does not use those parameter values. A `prepareStatement` method with scrollability, updatability, or holdability parameters applies only to preparation of SQL statements other than the CALL statement.

   The following table contains a list of valid values for *resultSetType* and *resultSetConcurrency*.

   Table 9. Valid combinations of resultSetType and resultSetConcurrency for ResultSets

***resultSetType* value**	***resultSetConcurrency* value**
`TYPE_FORWARD_ONLY`	`CONCUR_READ_ONLY`

Table 9. Valid combinations of resultSetType and resultSetConcurrency for ResultSets (continued)

***resultSetType* value**	***resultSetConcurrency* value**
TYPE_FORWARD_ONLY	CONCUR_UPDATABLE
TYPE_SCROLL_INSENSITIVE	CONCUR_READ_ONLY
TYPE_SCROLL_SENSITIVE"1.a" on page 45	CONCUR_READ_ONLY
TYPE_SCROLL_SENSITIVE"1.a" on page 45	CONCUR_UPDATABLE

Note:

a. This value does not apply to connections to IBM Informix.

resultSetHoldability has two possible values: HOLD_CURSORS_OVER_COMMIT and CLOSE_CURSORS_AT_COMMIT. Either of these values can be specified with any valid combination of *resultSetConcurrency* and *resultSetHoldability*. The value that you set overrides the default holdability for the connection.

Restriction: If the ResultSet is scrollable, and the ResultSet is used to select columns from a table on a Db2 on Linux, UNIX, and Windows systems server, the SELECT list of the SELECT statement that defines the ResultSet cannot include columns with the following data types:

- LONG VARCHAR
- LONG VARGRAPHIC
- BLOB
- CLOB
- XML
- A distinct type that is based on any of the previous data types in this list
- A structured type

2. If the SELECT statement has input parameters, invoke setXXX methods to pass values to the input parameters.
3. Invoke the executeQuery method to obtain the result table from the SELECT statement in a ResultSet object.
4. For each row that you want to access:
   a) Position the cursor using one of the methods that are listed in the following table.

   Restriction: If *resultSetType* is TYPE_FORWARD_ONLY, only ResultSet.next is valid.

   Table 10. ResultSet methods for positioning a scrollable cursor

Method	**Positions the cursor**
first"4.a.i" on page 46	On the first row of the ResultSet
last"4.a.i" on page 46	On the last row of the ResultSet
next"4.a.ii" on page 46	On the next row of the ResultSet
previous"4.a.i" on page 46,"4.a.iii" on page 46	On the previous row of the ResultSet
absolute(int *n*)"4.a.i" on page 46, "4.a.iv" on page 46	If *n*>0, on row *n* of the ResultSet. If *n*<0, and *m* is the number of rows in the ResultSet, on row *m+n+1* of the ResultSet.
relative(int *n*)"4.a.i" on page 46, "4.a.v" on page 46,"4.a.vi" on page 46,	If *n*>0, on the row that is *n* rows after the current row. If *n*<0, on the row that is *n* rows before the current row. If *n*=0, on the current row.

Table 10. ResultSet methods for positioning a scrollable cursor (continued)

Method	Positions the cursor
`afterLast`[“4.a.i” on page 46]	After the last row in the `ResultSet`
`beforeFirst`[“4.a.i” on page 46]	Before the first row in the `ResultSet`

Notes:

i) This method does not apply to connections to IBM Informix.

ii) If the cursor is before the first row of the `ResultSet`, this method positions the cursor on the first row.

iii) If the cursor is after the last row of the `ResultSet`, this method positions the cursor on the last row.

iv) If the absolute value of *n* is greater than the number of rows in the result set, this method positions the cursor after the last row if *n* is positive, or before the first row if *n* is negative.

v) The cursor must be on a valid row of the `ResultSet` before you can use this method. If the cursor is before the first row or after the last row, the method throws an `SQLException`.

vi) Suppose that *m* is the number of rows in the `ResultSet` and *x* is the current row number in the `ResultSet`. If *n*>0 and *x*+*n*>*m*, the driver positions the cursor after the last row. If *n*<0 and *x*+*n*<1, the driver positions the cursor before the first row.

b) If you need to know the current cursor position, use the `getRow`, `isFirst`, `isLast`, `isBeforeFirst`, or `isAfterLast` method to obtain this information.

c) If you specified a *resultSetType* value of TYPE_SCROLL_SENSITIVE in step [“1” on page 44], and you need to see the latest values of the current row, invoke the `refreshRow` method.

Recommendation: Because refreshing the rows of a `ResultSet` can have a detrimental effect on the performance of your applications, you should invoke `refreshRow` *only* when you need to see the latest data.

d) Perform one or more of the following operations:

- To retrieve data from each column of the current row of the `ResultSet` object, use `getXXX` methods.
- To update the current row from the underlying table, use `updateXXX` methods to assign column values to the current row of the `ResultSet`. Then use `updateRow` to update the corresponding row of the underlying table. If you decide that you do not want to update the underlying table, invoke the `cancelRowUpdates` method instead of the `updateRow` method.

  The *resultSetConcurrency* value for the `ResultSet` must be `CONCUR_UPDATABLE` for you to use these methods.
- To delete the current row from the underlying table, use the `deleteRow` method. Invoking `deleteRow` causes the driver to replace the current row of the `ResultSet` with a hole.

  The *resultSetConcurrency* value for the `ResultSet` must be `CONCUR_UPDATABLE` for you to use this method.

5. Invoke the `close` method to close the `ResultSet` object.
6. Invoke the `close` method to close the `Statement` or `PreparedStatement` object.

Example

The following code demonstrates how to retrieve all rows from the employee table in reverse order, and update the phone number for employee number "000010". The numbers to the right of selected statements correspond to the previously-described steps.

```
String s;
String stmtsrc;
Connection con;
Statement stmt;
ResultSet rs;
…
stmt = con.createStatement(ResultSet.TYPE_SCROLL_SENSITIVE,
                           ResultSet.CONCUR_UPDATABLE);                1
                                        // Create a Statement object
                                        // for a scrollable, updatable
                                        // ResultSet
stmtsrc = "SELECT EMPNO, PHONENO FROM EMPLOYEE " +
          "FOR UPDATE OF PHONENO";
rs = stmt.executeQuery(stmtsrc);        // Create the ResultSet         3
rs.afterLast();                         // Position the cursor at the end of
                                        // the ResultSet                4a
while (rs.previous()) {                 // Position the cursor backward
 s = rs.getString("EMPNO");             // Retrieve the employee number 4d
                                        // (column 1 in the result
                                        // table)
 System.out.println("Employee number = " + s);
                                        // Print the column value
 if (s.compareTo("000010") == 0) {      // Look for employee 000010
  rs.updateString("PHONENO","4657");    // Update their phone number
  rs.updateRow();                       // Update the row
 }
}
rs.close();                             // Close the ResultSet          5
stmt.close();                           // Close the Statement          6
```

Figure 15. Using a scrollable cursor

Related tasks

“Retrieving data from tables using the Statement.executeQuery method” on page 38
To retrieve data from a table using a SELECT statement with no parameter markers, you can use the `Statement.executeQuery` method.

Multi-row SQL operations in JDBC applications
The IBM Data Server Driver for JDBC and SQLJ supports multi-row INSERT, UPDATE, and FETCH for connections to data sources that support these operations.

Multi-row INSERT

In JDBC applications, when you execute INSERT or MERGE statements that use parameter markers in a batch, if the data server supports multi-row INSERT, the IBM Data Server Driver for JDBC and SQLJ can transform the batch INSERT or MERGE operations into multi-row INSERT statements. Multi-row INSERT operations can provide better performance in the following ways:

- For local applications, multi-row INSERTs result in fewer accesses of the data server.
- For distributed applications, multi-row INSERTs result in fewer network operations.

You cannot execute a multi-row INSERT operation by including a multi-row INSERT statement in a statement string in your JDBC application.

Multi-row INSERT is used by default. You can use the `Connection` or `DataSource` property enableMultiRowInsertSupport to control whether multi-row INSERT is used. Multi-row INSERT cannot be used for INSERT FROM SELECT statements that are executed in a batch.

Multi-row FETCH

Multi-row FETCH can provide better performance than retrieving one row with each FETCH statement. For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, multi-row FETCH can be used for forward-only cursors and scrollable cursors. For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, multi-row FETCH can be used only for scrollable cursors.

When you retrieve data in your applications, the IBM Data Server Driver for JDBC and SQLJ determines whether to use multi-row FETCH, depending on several factors:

- The setting of the enableRowsetSupport property
- The setting of the useRowsetCursor property, for connections to Db2 for z/OS
- The type of IBM Data Server Driver for JDBC and SQLJ connectivity that is being used
- The version of the IBM Data Server Driver for JDBC and SQLJ

For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS, one of the following sets of conditions must be true for multi-row FETCH to be used.

- First set of conditions:
  - The IBM Data Server Driver for JDBC and SQLJ version is 3.51 or later.
  - The enableRowsetSupport property value is com.ibm.db2.jcc.DB2BaseDataSource.YES (1), **or** the enableRowsetSupport property value is com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0) and the useRowsetCursor property value is `true`.
  - The FETCH operation uses a scrollable cursor.

    For forward-only cursors, fetching of multiple rows might occur through DRDA block FETCH. However, this behavior does not utilize the data source's multi-row FETCH capability.
- Second set of conditions:
  - The IBM Data Server Driver for JDBC and SQLJ version is 3.1.
  - The useRowsetCursor property value is com.ibm.db2.jcc.DB2BaseDataSource.YES (1).
  - The FETCH operation uses a scrollable cursor.

    For forward-only cursors, fetching of multiple rows might occur through DRDA block FETCH. However, this behavior does not utilize the data source's multi-row FETCH capability.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS the following conditions must be true for multi-row FETCH to be used.

- The IBM Data Server Driver for JDBC and SQLJ version is 3.51 or later.
- The enableRowsetSupport property value is com.ibm.db2.jcc.DB2BaseDataSource.YES (1).
- The FETCH operation uses a scrollable cursor or a forward-only cursor.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, you can control the maximum size of a rowset for each statement by setting the maxRowsetSize property.

Multi-row positioned UPDATE or DELETE

The IBM Data Server Driver for JDBC and SQLJ supports a technique for performing positioned update or delete operations that follows the JDBC 1 standard. That technique involves using the `ResultSet.getCursorName` method to obtain the name of the cursor for the `ResultSet`, and defining a positioned UPDATE or positioned DELETE statement of the following form:

```
UPDATE table SET col1=value1,…coln=valueN WHERE CURRENT OF cursorname
DELETE FROM table WHERE CURRENT OF cursorname
```

Multi-row UPDATE or DELETE when useRowsetCursor is set to `true`: If you use the JDBC 1 technique to update or delete data on a database server that supports multi-row FETCH, and multi-row FETCH is enabled through the useRowsetCursor property, the positioned UPDATE or DELETE statement might update or delete multiple rows, when you expect it to update or delete a single row. To avoid unexpected updates or deletes, you can take one of the following actions:

- Use an updatable `ResultSet` to retrieve and update one row at a time, as shown in the previous example.
- Set useRowsetCursor to `false`.

Multi-row UPDATE or DELETE when enableRowsetSupport is set to com.ibm.db2.jcc.DB2BaseDataSource.YES (1): The JDBC 1 technique for updating or deleting data is incompatible with multi-row FETCH that is enabled through the enableRowsetSupport property.

Recommendation: If your applications use the JDBC 1 technique, update them to use the JDBC 2.0 `ResultSet.updateRow` or `ResultSet.deleteRow` methods for positioned update or delete activity.

Testing whether the current row of a ResultSet is a delete hole or update hole in a JDBC application

If a `ResultSet` has the TYPE_SCROLL_SENSITIVE attribute, and the underlying cursor is SENSITIVE STATIC, you need to test for delete holes or update holes before you attempt to retrieve rows of the `ResultSet`.

About this task

After a SENSITIVE STATIC `ResultSet` is opened, it does not change size. This means that deleted rows are replaced by placeholders, which are also called *holes*. If updated rows no longer fit the criteria for the `ResultSet`, those rows also become holes. You cannot retrieve rows that are holes.

Procedure

To test whether the current row in a `ResultSet` is a delete hole or update hole, follow these steps:

1. Call the `DatabaseMetaData.deletesAreDetected` or `DatabaseMetaData.updatesAreDetected` method with the TYPE_SCROLL_SENSITIVE argument to determine whether the data source creates holes for a TYPE_SCROLL_SENSITIVE `ResultSet`.
2. If `DatabaseMetaData.deletesAreDetected` or `DatabaseMetaData.updatesAreDetected` returns `true`, which means that the data source can create holes, call the `ResultSet.rowDeleted` or `ResultSet.rowUpdated` method to determine whether the current row is a delete or update hole.

   If the method returns `true`, the current row is a hole.

Example

The following code tests whether the current row is a delete hole.

```
Statement stmt = con.createStatement(ResultSet.TYPE_SCROLL_SENSITIVE,
  ResultSet.CONCUR_UPDATABLE);
                                       // Create a Statement object
                                       // for a scrollable, updatable
                                       // ResultSet
ResultSet rs =
  stmt.executeQuery("SELECT EMPNO FROM EMPLOYEE FOR UPDATE OF PHONENO");
                                       // Create the ResultSet
DatabaseMetaData dbmd = con.getMetaData();
                                       // Create the DatabaseMetaData object
boolean dbSeesDeletes =
  dbmd.deletesAreDetected(ResultSet.TYPESCROLL_SENSITIVE);
                                       // Can the database see delete holes?
rs.afterLast();                        // Position the cursor at the end of
                                       // the ResultSet
while (rs.previous()) {                // Position the cursor backward
 if (dbSeesDeletes) {                  // If delete holes can be detected
   if (!(rs.rowDeleted()))             // If this row is not a delete hole
   {
     s = rs.getString("EMPNO");        // Retrieve the employee number
     System.out.println("Employee number = " + s);
                                       // Print the column value
   }
  }
}
rs.close();                            // Close the ResultSet
stmt.close();                          // Close the Statement
```

Inserting a row into a ResultSet in a JDBC application

If a ResultSet has a *resultSetConcurrency* attribute of CONCUR_UPDATABLE, you can insert rows into the ResultSet.

Before you begin

Ensure that the enableExtendedDescribe property is not set, or is set to DB2BaseDataSource.YES (2). Insertion of a row into a ResultSet does not work unless extended describe capability is enabled.

Procedure

1. Perform the following steps for each row that you want to insert.
   a) Call the ResultSet.moveToInsertRow method to create the row that you want to insert. The row is created in a buffer outside the ResultSet.

      If an insert buffer already exists, all old values are cleared from the buffer.

   b) Call ResultSet.updateXXX methods to assign values to the row that you want to insert.

      You need to assign a value to at least one column in the ResultSet. If you do not do so, an SQLException is thrown when the row is inserted into the ResultSet.

      If you do not assign a value to a column of the ResultSet, when the underlying table is updated, the data source inserts the default value for the associated table column.

      If you assign a null value to a column that is defined as NOT NULL, the JDBC driver throws and SQLException.

   c) Call ResultSet.insertRow to insert the row into the ResultSet.

      After you call ResultSet.insertRow, all values are always cleared from the insert buffer, even if ResultSet.insertRow fails.
2. Reposition the cursor within the ResultSet.

   To move the cursor from the insert row to the ResultSet, you can invoke any of the methods that position the cursor at a specific row, such as ResultSet.first, ResultSet.absolute, or ResultSet.relative. Alternatively, you can call ResultSet.moveToCurrentRow to move the cursor to the row in the ResultSet that was the current row before the insert operation occurred.

   After you call ResultSet.moveToCurrentRow, all values are cleared from the insert buffer.

Example

The following code illustrates inserting a row into a ResultSet that consists of all rows in the sample DEPARTMENT table. After the row is inserted, the code places the cursor where it was located in the ResultSet before the insert operation. The numbers to the right of selected statements correspond to the previously-described steps.

```
stmt = con.createStatement(ResultSet.TYPE_SCROLL_SENSITIVE,
               ResultSet.CONCUR_UPDATABLE);
ResultSet rs = stmt.executeQuery("SELECT * FROM DEPARTMENT");
rs.moveToInsertRow();                                    1a
rs.updateString("DEPT_NO", "M13");                       1b
rs.updateString("DEPTNAME", "TECHNICAL SUPPORT");
rs.updateString("MGRNO", "000010");
rs.updateString("ADMRDEPT", "A00");
rs.insertRow();                                          1c
rs.moveToCurrentRow();                                   2
```

Testing whether the current row was inserted into a ResultSet in a JDBC application

If a `ResultSet` is dynamic, you can insert rows into it. After you insert rows into a `ResultSet` you might need to know which rows were inserted.

Procedure

To test whether the current row in a `ResultSet` was inserted, follow these steps:

1. Call the `DatabaseMetaData.ownInsertsAreVisible` and `DatabaseMetaData.othersInsertsAreVisible` methods to determine whether inserts can be visible to the given type of `ResultSet`.
2. If inserts can be visible to the `ResultSet`, call the `DatabaseMetaData.insertsAreDetected` method to determine whether the given type of `ResultSet` can detect inserts.
3. If the `ResultSet` can detect inserts, call the `ResultSet.rowInserted` method to determine whether the current row was inserted.

Calling stored procedures in JDBC applications

To call stored procedures, you invoke methods in the `CallableStatement` or `PreparedStatement` class.

Procedure

The basic steps for calling a stored procedures using standard `CallableStatement` methods are:

1. Invoke the `Connection.prepareCall` method with the CALL statement as its argument to create a `CallableStatement` object.

   You can represent parameters with standard parameter markers (?) or named parameter markers. You cannot mix named parameter markers with standard parameter markers in the same CALL statement.

   Restriction: The parameter types that are permitted depend on whether the data source supports dynamic execution of the CALL statement. Db2 for z/OS does not support dynamic execution of the CALL statement. For a call to a stored procedure that is on a Db2 for z/OS database server, the parameters can be parameter markers or literals, but not expressions. Even if all parameters are literals, you cannot use `Statement` methods to execute CALL statements. You must use `PreparedStatement` methods or `CallableStatement` methods. The following table lists the types of literals that are supported, and the JDBC types to which they map.

Table 11. Supported literal types in parameters in Db2 for z/OS stored procedure calls

Literal parameter type	JDBC type	Examples
Integer	java.sql.Types.INTEGER	-122, 40022, +27
Floating-point decimal	java.sql.Types.DOUBLE	23E12, 40022E-4, +2723E+15, 1E+23, 0E0
Fixed-point decimal	java.sql.Types.DECIMAL	-23.12, 40022.4295, 0.0, +2723.23, 10000000000
Character	java.sql.Types.VARCHAR	'Grantham Lutz', 'O''Conner', 'ABcde?z?'
Hexadecimal	java.sql.Types.VARBINARY	X'C1C30427', X'00CF18E0'
Unicode string	java.sql.Types.VARCHAR	UX'0041', UX'0054006500730074'

Important: In a `prepareCall` method invocation, you cannot specify the scrollability, updatability, or holdability of result sets that are returned from a stored procedure. Those characteristics are determined by the stored procedure code, when it declares the cursors for the result sets that are returned. If you specify any of the forms of `prepareCall` that include scrollability, updatability, or holdability parameters, the IBM Data Server Driver for JDBC and SQLJ does not use those parameter

values. A `prepareCall` method with scrollability, updatability, or holdability parameters applies only to preparation of SQL statements other than the CALL statement.

2. Invoke the `CallableStatement.setXXX` methods to pass values to the input parameters (parameters that are defined as IN or INOUT in the CREATE PROCEDURE statement).

   This step assumes that you use standard parameter markers or named parameters. Alternatively, if you use named parameter markers, you use IBM Data Server Driver for JDBC and SQLJ-only methods to pass values to the input parameters.

   Restriction: If the data source does not support dynamic execution of the CALL statement, you must specify the data types for CALL statement input parameters **exactly** as they are specified in the stored procedure definition.

   Restriction: Invoking `CallableStatement.setXXX` methods to pass values to the OUT parameters is not supported. There is no need to set values for the OUT parameters of a stored procedure because the stored procedure does not use those values.

3. Invoke the `CallableStatement.registerOutParameter` method to register parameters that are defined as OUT in the CREATE PROCEDURE statement with specific data types.

   This step assumes that you use standard parameter markers. Alternatively, if you use named parameter markers, you use IBM Data Server Driver for JDBC and SQLJ-only methods to register OUT parameters with specific data types.

   Restriction: If the data source does not support dynamic execution of the CALL statement, you must specify the data types for CALL statement OUT, IN, or INOUT parameters **exactly** as they are specified in the stored procedure definition.

4. Invoke one of the following methods to call the stored procedure:

   `CallableStatement.executeUpdate`
   Invoke this method if the stored procedure does not return result sets.

   `CallableStatement.executeQuery`
   Invoke this method if the stored procedure returns one result set.

   You can invoke `CallableStatement.executeQuery` for a stored procedure that returns no result sets if you set property allowNullResultSetForExecuteQuery to `DB2BaseDataSource.YES` (1). In that case, `CallableStatement.executeQuery` returns null. This behavior does not conform to the JDBC standard.

   `CallableStatement.execute`
   Invoke this method if the stored procedure returns multiple result sets, or an unknown number of result sets.

   Restriction: IBM Informix data sources do not support multiple result sets.

5. If the stored procedure returns multiple result sets, retrieve the result sets.

   Restriction: IBM Informix data sources do not support multiple result sets.

6. Invoke the `CallableStatement.getXXX` methods to retrieve values from the OUT parameters or INOUT parameters.
7. Invoke the `CallableStatement.close` method to close the `CallableStatement` object when you have finished using that object.

Example

The following code illustrates calling a stored procedure that has one input parameter, four output parameters, and no returned `ResultSets`. The numbers to the right of selected statements correspond to the previously-described steps.

```
int ifcaret;
int ifcareas;
int xsbytes;
String errbuff;
Connection con;
```

```
CallableStatement cstmt;
ResultSet rs;
…
cstmt = con.prepareCall("CALL DSN8.DSN8ED2(?,?,?,?,?)");                1
                                  // Create a CallableStatement object
cstmt.setString (1, "DISPLAY THREAD(*)");                               2
                                  // Set input parameter (Db2 command)
cstmt.registerOutParameter (2, Types.INTEGER);                          3
                                  // Register output parameters
cstmt.registerOutParameter (3, Types.INTEGER);
cstmt.registerOutParameter (4, Types.INTEGER);
cstmt.registerOutParameter (5, Types.VARCHAR);
cstmt.executeUpdate();            // Call the stored procedure          4
ifcaret = cstmt.getInt(2);        // Get the output parameter values    6
ifcareas = cstmt.getInt(3);
xsbytes = cstmt.getInt(4);
errbuff = cstmt.getString(5);
cstmt.close();                                                          7
```

Related tasks

“Using named parameter markers with CallableStatement objects” on page 78
You can use named parameter markers instead of standard parameter markers in `CallableStatement` objects to assign values to IN or INOUT parameters and to register OUT parameters.

Related reference

“Driver support for JDBC APIs” on page 318
The JDBC drivers that are supported by Db2 and IBM Informix database systems have different levels of support for JDBC methods.

Retrieving multiple result sets from a stored procedure in a JDBC application

If you call a stored procedure that returns result sets, you need to include code to retrieve the result sets.

About this task

The steps that you take depend on whether you know how many result sets are returned, and whether you know the contents of those result sets.

Related tasks

“Retrieving data from tables using the Statement.executeQuery method” on page 38
To retrieve data from a table using a SELECT statement with no parameter markers, you can use the `Statement.executeQuery` method.

“Retrieving data from tables using the PreparedStatement.executeQuery method” on page 39
To retrieve data from a table using a SELECT statement with parameter markers, you use the `PreparedStatement.executeQuery` method.

“Calling stored procedures in JDBC applications” on page 51
To call stored procedures, you invoke methods in the `CallableStatement` or `PreparedStatement` class.

Retrieving a known number of result sets from a stored procedure in a JDBC application

Retrieving a known number of result sets from a stored procedure is a simpler procedure than retrieving an unknown number of result sets.

Procedure

To retrieve result sets when you know the number of result sets and their contents, follow these steps:

1. Invoke the `Statement.execute` method, the `PreparedStatement.execute` method, or the `CallableStatement.execute` method to call the stored procedure.

   Use `PreparedStatement.execute` if the stored procedure has input parameters.
2. Invoke the `getResultSet` method to obtain the first result set, which is in a `ResultSet` object.
3. In a loop, position the cursor using the `next` method, and retrieve data from each column of the current row of the `ResultSet` object using `getXXX` methods.

4. If there are *n* result sets, repeat the following steps *n*-1 times:
   a) Invoke the `getMoreResults` method to close the current result set and point to the next result set.
   b) Invoke the `getResultSet` method to obtain the next result set, which is in a `ResultSet` object.
   c) In a loop, position the cursor using the `next` method, and retrieve data from each column of the current row of the `ResultSet` object using `getXXX` methods.

Example

The following code illustrates retrieving two result sets. The first result set contains an INTEGER column, and the second result set contains a CHAR column. The numbers to the right of selected statements correspond to the previously described steps.

```
CallableStatement cstmt;
ResultSet rs;
int i;
String s;
…
cstmt.execute();                        // Call the stored procedure      1
rs = cstmt.getResultSet();              // Get the first result set       2
while (rs.next()) {                     // Position the cursor            3
 i = rs.getInt(1);                      // Retrieve current result set value
 System.out.println("Value from first result set = " + i);
                                        // Print the value
}
cstmt.getMoreResults();                 // Point to the second result set 4a
                                        // and close the first result set
rs = cstmt.getResultSet();              // Get the second result set      4b
while (rs.next()) {                     // Position the cursor            4c
 s = rs.getString(1);                   // Retrieve current result set value
 System.out.println("Value from second result set = " + s);
                                        // Print the value
}
rs.close();                             // Close the result set
cstmt.close();                          // Close the statement
```

Retrieving an unknown number of result sets from a stored procedure in a JDBC application

Retrieving an unknown number of result sets from a stored procedure is a more complicated procedure than retrieving a known number of result sets.

About this task

To retrieve result sets when you do not know the number of result sets or their contents, you need to retrieve `ResultSets`, until no more `ResultSets` are returned. For each `ResultSet`, use `ResultSetMetaData` methods to determine its contents.

After you call a stored procedure, follow these basic steps to retrieve the contents of an unknown number of result sets.

Procedure

1. Check the value that was returned from the `execute` statement that called the stored procedure.

   If the returned value is `true`, there is at least one result set, so you need to go to the next step.
2. Repeat the following steps in a loop:
   a) Invoke the `getResultSet` method to obtain a result set, which is in a `ResultSet` object. Invoking this method closes the previous result set.
   b) Use `ResultSetMetaData` methods to determine the contents of the `ResultSet`, and retrieve data from the `ResultSet`.
   c) Invoke the `getMoreResults` method to determine whether there is another result set. If `getMoreResults` returns `true`, go to step “1” on page 54 to get the next result set.

Example

The following code illustrates retrieving result sets when you do not know the number of result sets or their contents. The numbers to the right of selected statements correspond to the previously described steps.

```
CallableStatement cstmt;
ResultSet rs;
…
boolean resultsAvailable = cstmt.execute(); // Call the stored procedure
while (resultsAvailable) {                  // Test for result sets      1
 ResultSet rs = cstmt.getResultSet();       // Get a result set          2a
 …                                          // Process the ResultSet
                                            // as you would process
                                            // a ResultSet from a table
 resultsAvailable = cstmt.getMoreResults(); // Check for next result set 2c
                                            // (Also closes the
                                            // previous result set)
}
```

Related tasks

“Learning about a ResultSet using ResultSetMetaData methods” on page 41
You cannot always know the number of columns and data types of the columns in a table or result set. This is true especially when you are retrieving data from a remote data source.

Keeping result sets open when retrieving multiple result sets from a stored procedure in a JDBC application

The `getMoreResults` method has a form that lets you leave the current `ResultSet` open when you open the next `ResultSet`.

Procedure

When you call `getMoreResults` to check for the next `ResultSet`, use this form:

```
CallableStatement.getMoreResults(int current);
```

- To keep the current `ResultSet` open when you check for the next `ResultSet`, specify a value of `Statement.KEEP_CURRENT_RESULT` for *current*.
- To close the current `ResultSet` when you check for the next `ResultSet`, specify a value of `Statement.CLOSE_CURRENT_RESULT` for *current*.
- To close **all** `ResultSet` objects, specify a value of `Statement.CLOSE_ALL_RESULTS` for *current*.

Example

The following code keeps all `ResultSets` open until the final `ResultSet` has been retrieved, and then closes all `ResultSets`.

```
CallableStatement cstmt;
…
boolean resultsAvailable = cstmt.execute(); // Call the stored procedure
if (resultsAvailable==true) {               // Test for result set
 ResultSet rs1 = cstmt.getResultSet();      // Get a result set
 …
 resultsAvailable = cstmt.getMoreResults(Statement.KEEP_CURRENT_RESULT);
                                            // Check for next result set
                                            // but do not close
                                            // previous result set
 if (resultsAvailable==true) {              // Test for another result set
  ResultSet rs2 = cstmt.getResultSet();     // Get next result set
  …                                         // Process either ResultSet
 }
}
resultsAvailable = cstmt.getMoreResults(Statement.CLOSE_ALL_RESULTS);
                                            // Close the result sets
```

LOBs in JDBC applications with the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ supports methods for updating and retrieving data from BLOB, CLOB, and DBCLOB columns in a table, and for calling stored procedures or user-defined functions with BLOB or CLOB parameters.

Related reference

"Driver support for JDBC APIs" on page 318
The JDBC drivers that are supported by Db2 and IBM Informix database systems have different levels of support for JDBC methods.

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

Progressive streaming with the IBM Data Server Driver for JDBC and SQLJ

If the data source supports progressive streaming, also known as dynamic data format, the IBM Data Server Driver for JDBC and SQLJ can use progressive streaming to retrieve data in LOB or XML columns.

Db2 for z/OS Version 9.1 and later supports progressive streaming for LOBs and XML objects. Db2 on Linux, UNIX, and Windows systems Version 9.5 and later, IBM Informix Version 11.50 and later, and Db2 for IBM i V6R1 and later support progressive streaming for LOBs.

With progressive streaming, the data source dynamically determines the most efficient mode in which to return LOB or XML data, based on the size of the LOBs or XML objects.

Progressive streaming is the default behavior in the following environments:

MinimumIBM Data Server Driver for JDBC and SQLJ version	Minimum data server version	Types of objects
3.53	Db2 for IBM i V6R1	LOB, XML
3.50	Db2 on Linux, UNIX, and Windows systems Version 9.5	LOB
3.50	IBM Informix Version 11.50	LOB
3.2	Db2 for z/OS Version 9	LOB, XML

You set the progressive streaming behavior on new connections using the IBM Data Server Driver for JDBC and SQLJ progressiveStreaming property.

For Db2 for z/OS Version 9.1 and later data sources, or Db2 on Linux, UNIX, and Windows systems Version 9.5 and later data sources, you can set the progressive streaming behavior for existing connections with the **`DB2Connection.setDBProgressiveStreaming(DB2BaseDataSource.YES)`** method. If you call **`DB2Connection.setDBProgressiveStreaming(DB2BaseDataSource.YES)`**, all `ResultSet` objects that are created on the connection use progressive streaming behavior.

When progressive streaming is enabled, you can control when the JDBC driver materializes LOBs with the streamBufferSize property. If a LOB or XML object is less than or equal to the streamBufferSize value, the object is materialized.

A LOB object is also materialized when an application program performs any of the following actions, regardless of the progressiveStreaming or streamBufferSize settings:

- Invokes a user-defined function with a LOB value as an argument
- Calls a stored procedure with a LOB value as an input or output argument
- Assigns a LOB host variable to a LOB locator host variable

Important: With progressive streaming, when you retrieve a LOB or XML value from a `ResultSet` into an application variable, you can manipulate the contents of that application variable until you move

the cursor or close the cursor on the ResultSet. After that, the contents of the application variable are no longer available to you. If you perform any actions on the LOB in the application variable, you receive an SQLException. For example, suppose that progressive streaming is enabled, and you execute statements like this:

```
…
ResultSet rs = stmt.executeQuery("SELECT CLOBCOL FROM MY_TABLE");
rs.next();                // Retrieve the first row of the ResultSet
Clob clobFromRow1  = rs.getClob(1);
                          // Put the CLOB from the first column of
                          // the first row in an application variable
String substr1Clob = clobFromRow1.getSubString(1,50);
                          // Retrieve the first 50 bytes of the CLOB
rs.next();                // Move the cursor to the next row.
                          // clobFromRow1 is no longer available.
// String substr2Clob = clobFromRow1.getSubString(51,100);
                          // This statement would yield an SQLException
Clob clobFromRow2  = rs.getClob(1);
                          // Put the CLOB from the first column of
                          // the second row in an application variable
rs.close();               // Close the ResultSet.
                          // clobFromRow2 is also no longer available.
```

After you execute rs.next() to position the cursor at the second row of the ResultSet, the CLOB value in clobFromRow1 is no longer available to you. Similarly, after you execute rs.close() to close the ResultSet, the values in clobFromRow1 and clobFromRow2 are no longer available.

If you disable progressive streaming, the way in which the IBM Data Server Driver for JDBC and SQLJ handles LOBs depends on the value of the fullyMaterializeLobData property.

Use of progressive streaming is the preferred method of LOB or XML data retrieval.

LOB locators with the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ can use LOB locators to retrieve data in LOB columns.

To cause JDBC to use LOB locators to retrieve data from LOB columns, you need to set the fullyMaterializeLobData property to false and set the progressiveStreaming property to NO (DB2BaseDataSource.NO in an application program).

The effect of fullyMaterializeLobData depends on whether the data source supports progressive streaming and the value of the progressiveStreaming property:

- If the data source does not support progressive locators:

  If the value of fullyMaterializeLobData is true, LOB data is fully materialized within the JDBC driver when a row is fetched. If the value is false, LOB data is streamed. The driver uses locators internally to retrieve LOB data in chunks on an as-needed basis It is highly recommended that you set this value to false when you retrieve LOBs that contain large amounts of data. The default is true.
- If the data source supports progressive streaming, also known as dynamic data format:

  The JDBC driver ignores the value of fullyMaterializeLobData if the progressiveStreaming property is set to YES (DB2BaseDataSource.YES in an application program) or is not set.

fullyMaterializeLobData has no effect on stored procedure parameters.

As in any other language, a LOB locator in a Java application is associated with only one data source. You cannot use a single LOB locator to move data between two different data sources. To move LOB data between two data sources, you need to materialize the LOB data when you retrieve it from a table in the first data source and then insert that data into the table in the second data source.

LOB operations with the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ supports methods for updating and retrieving data from BLOB, CLOB, and DBCLOB columns in a table, and for calling stored procedures or user-defined functions with BLOB or CLOB parameters.

Among the operations that you can perform on LOB data under the IBM Data Server Driver for JDBC and SQLJ are:

- Specify a BLOB or column as an argument of the following `ResultSet` methods to retrieve data from a BLOB or CLOB column:

  For BLOB columns:

  - `getBinaryStream`
  - `getBlob`
  - `getBytes`

  For CLOB columns:

  - `getAsciiStream`
  - `getCharacterStream`
  - `getClob`
  - `getString`
- Call the following `ResultSet` methods to update a BLOB or CLOB column in an updatable `ResultSet`:

  For BLOB columns:

  - `updateBinaryStream`
  - `updateBlob`

  For CLOB columns:

  - `updateAsciiStream`
  - `updateCharacterStream`
  - `updateClob`

  If you specify -1 for the *length* parameter in any of the previously listed methods, the IBM Data Server Driver for JDBC and SQLJ reads the input data until it is exhausted.
- Use the following `PreparedStatement` methods to set the values for parameters that correspond to BLOB or CLOB columns:

  For BLOB columns:

  - `setBytes`
  - `setBlob`
  - `setBinaryStream`
  - `setObject`, where the *Object* parameter value is an `InputStream`.

  For CLOB columns:

  - `setString`
  - `setAsciiStream`
  - `setClob`
  - `setCharacterStream`
  - `setObject`, where the *Object* parameter value is a `Reader`.

  If you specify -1 for *length*, the IBM Data Server Driver for JDBC and SQLJ reads the input data until it is exhausted.
- Retrieve the value of a JDBC `CLOB` parameter using the `CallableStatement.getString` method.

Restriction: With IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, you cannot call a stored procedure that has DBCLOB OUT or INOUT parameters.

If you are using the IBM Data Server Driver for JDBC and SQLJ version 4.0 or later, you can perform the following additional operations:

- Use `ResultSet.updateXXX` or `PreparedStatement.setXXX` methods to update a BLOB or CLOB with a *length* value of up to 2GB for a BLOB or CLOB. For example, these methods are defined for BLOBs:

```
ResultSet.updateBlob(int columnIndex, InputStream x, long length)
ResultSet.updateBlob(String columnLabel, InputStream x, long length)
ResultSet.updateBinaryStream(int columnIndex, InputStream x, long length)
ResultSet.updateBinaryStream(String columnLabel, InputStream x, long length)
PreparedStatement.setBlob(int columnIndex, InputStream x, long length)
PreparedStatement.setBlob(String columnLabel, InputStream x, long length)
PreparedStatement.setBinaryStream(int columnIndex, InputStream x, long length)
PreparedStatement.setBinaryStream(String columnLabel, InputStream x, long length)
```

- Use `ResultSet.updateXXX` or `PreparedStatement.setXXX` methods without the *length* parameter when you update a BLOB or CLOB, to cause the IBM Data Server Driver for JDBC and SQLJ to read the input data until it is exhausted. For example:

```
ResultSet.updateBlob(int columnIndex, InputStream x)
ResultSet.updateBlob(String columnLabel, InputStream x)
ResultSet.updateBinaryStream(int columnIndex, InputStream x)
ResultSet.updateBinaryStream(String columnLabel, InputStream x)
PreparedStatement.setBlob(int columnIndex, InputStream x)
PreparedStatement.setBlob(String columnLabel, InputStream x)
PreparedStatement.setBinaryStream(int columnIndex, InputStream x)
PreparedStatement.setBinaryStream(String columnLabel, InputStream x)
```

- Create a `Blob` or `Clob` object that contains no data, using the `Connection.createBlob` or `Connection.createClob` method.
- Materialize a `Blob` or `Clob` object on the client, when progressive streaming or locators are in use, using the `Blob.getBinaryStream` or `Clob.getCharacterStream` method.
- Free the resources that a `Blob` or `Clob` object holds, using the `Blob.free` or `Clob.free` method.

Java data types for retrieving or updating LOB column data in JDBC applications

When the JDBC driver cannot immediately determine the data type of a parameter that is used with a LOB column, you need to choose a parameter data type that is compatible with the LOB data type.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS, when the JDBC driver processes a `CallableStatement.setXXX` call for a stored procedure input parameter, or a `CallableStatement.registerOutParameter` call for a stored procedure output parameter, the driver cannot determine the parameter data types.

When the deferPrepares property is set to true, and the IBM Data Server Driver for JDBC and SQLJ processes a `PreparedStatement.setXXX` call, the driver might need to do extra processing to determine data types. This extra processing can impact performance.

Input parameters for BLOB columns

For IN parameters for BLOB columns, or INOUT parameters that are used for input to BLOB columns, you can use one of the following techniques:

- Use a java.sql.Blob input variable, which is an exact match for a BLOB column:

```
cstmt.setBlob(parmIndex, blobData);
```

- Use a `CallableStatement.setObject` call that specifies that the target data type is BLOB:

```
byte[] byteData = {(byte)0x1a, (byte)0x2b, (byte)0x3c};
cstmt.setObject(parmInd, byteData, java.sql.Types.BLOB);
```

- Use an input parameter of type of `java.io.ByteArrayInputStream` with a `CallableStatement.setBinaryStream` call. A `java.io.ByteArrayInputStream` object is compatible with a BLOB data type. For this call, you need to specify the exact length of the input data:

```
java.io.ByteArrayInputStream byteStream =
  new java.io.ByteArrayInputStream(byteData);
int numBytes = byteData.length;
cstmt.setBinaryStream(parmIndex, byteStream, numBytes);
```

Output parameters for BLOB columns

For OUT parameters for BLOB columns, or INOUT parameters that are used for output from BLOB columns, you can use the following technique:

- Use the `CallableStatement.registerOutParameter` call to specify that an output parameter is of type BLOB. Then you can retrieve the parameter value into any variable that has a data type that is compatible with a BLOB data type. For example, the following code lets you retrieve a BLOB value into a byte[] variable:

```
cstmt.registerOutParameter(parmIndex, java.sql.Types.BLOB);
cstmt.execute();
byte[] byteData = cstmt.getBytes(parmIndex);
```

Input parameters for CLOB columns

For IN parameters for CLOB columns, or INOUT parameters that are used for input to CLOB columns, you can use one of the following techniques:

- Use a java.sql.Clob input variable, which is an exact match for a CLOB column:

```
cstmt.setClob(parmIndex, clobData);
```

- Use a `CallableStatement.setObject` call that specifies that the target data type is CLOB:

```
String charData = "CharacterString";
cstmt.setObject(parmInd, charData, java.sql.Types.CLOB);
```

- Use one of the following types of stream input parameters:
  - A `java.io.StringReader` input parameter with a `cstmt.setCharacterStream` call:

    ```
    java.io.StringReader reader = new java.io.StringReader(charData);
    cstmt.setCharacterStream(parmIndex, reader, charData.length);
    ```

  - A `java.io.ByteArrayInputStream` parameter with a `cstmt.setAsciiStream` call, for ASCII data:

    ```
    byte[] charDataBytes = charData.getBytes("US-ASCII");
    java.io.ByteArrayInputStream byteStream =
      new java.io.ByteArrayInputStream (charDataBytes);
    cstmt.setAsciiStream(parmIndex, byteStream, charDataBytes.length);
    ```

    For these calls, you need to specify the exact length of the input data.
- Use a String input parameter with a `cstmt.setString` call:

```
cstmt.setString(parmIndex, charData);
```

  If the length of the data is greater than 32KB, and the JDBC driver has no DESCRIBE information about the parameter data type, the JDBC driver assigns the CLOB data type to the input data.
- Use a String input parameter with a `cstmt.setObject` call, and specify the target data type as VARCHAR or LONGVARCHAR:

```
cstmt.setObject(parmIndex, charData, java.sql.Types.VARCHAR);
```

If the length of the data is greater than 32KB, and the JDBC driver has no DESCRIBE information about the parameter data type, the JDBC driver assigns the CLOB data type to the input data.

Output parameters for CLOB columns

For OUT parameters for CLOB columns, or INOUT parameters that are used for output from CLOB columns, you can use one of the following techniques:

- Use the `CallableStatement.registerOutParameter` call to specify that an output parameter is of type CLOB. Then you can retrieve the parameter value into a Clob variable. For example:

```
cstmt.registerOutParameter(parmIndex, java.sql.Types.CLOB);
cstmt.execute();
Clob clobData = cstmt.getClob(parmIndex);
```

- Use the `CallableStatement.registerOutParameter` call to specify that an output parameter is of type VARCHAR or LONGVARCHAR:

```
cstmt.registerOutParameter(parmIndex, java.sql.Types.VARCHAR);
cstmt.execute();
String charData = cstmt.getString(parmIndex);
```

  This technique should be used only if you know that the length of the retrieved data is less than or equal to 32KB. Otherwise, the data is truncated.

Related concepts

"LOBs in JDBC applications with the IBM Data Server Driver for JDBC and SQLJ" on page 56
The IBM Data Server Driver for JDBC and SQLJ supports methods for updating and retrieving data from BLOB, CLOB, and DBCLOB columns in a table, and for calling stored procedures or user-defined functions with BLOB or CLOB parameters.

Related reference

"Data types that map to database data types in Java applications" on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

ROWIDs in JDBC with the IBM Data Server Driver for JDBC and SQLJ

Db2 for z/OS and Db2 for IBM i support the ROWID data type for a column in a database table. A ROWID is a value that uniquely identifies a row in a table.

Although IBM Informix also supports rowids, those rowids have the INTEGER data type. You can select an IBM Informix rowid column into a variable with a four-byte integer data type.

You can use the following `ResultSet` methods to retrieve data from a ROWID column:

- `getBytes`
- `getColumns (JDBC 4.0 and later)`
- `getObject`
- `getRowId` (JDBC 4.0 and later)

You can use the following `ResultSet` method to update a ROWID column of an updatable `ResultSet`:

- `updateRowId` (JDBC 4.0 and later)

  `updateRowId` is valid only if the target database system supports updating of ROWID columns.

In JDBC 4.0, for `getObject`, the IBM Data Server Driver for JDBC and SQLJ returns an instance of the class `java.sql.RowId`.

You can use the following `PreparedStatement` methods to set a value for a parameter that is associated with a ROWID column:

- `setRowId` (JDBC 4.0 and later)

- setBytes
- setObject

In JDBC 4.0, for setObject, use the type java.sql.Types.ROWID or an instance of the java.sql.RowId class as the target type for the parameter.

You can use the following CallableStatement methods to retrieve a ROWID column as an output parameter from a stored procedure call:

- getRowId (JDBC 4.0 and later)
- getObject

To call a stored procedure that is defined with a ROWID output parameter, register that parameter to be of the java.sql.Types.ROWID type.

ROWID values are valid for different periods of time, depending on the data source on which those ROWID values are defined. Use the DatabaseMetaData.getRowIdLifetime method to determine the time period for which a ROWID value is valid. The values that are returned for the data sources are listed in the following table.

Table 12. DatabaseMetaData.getRowIdLifetime values for supported data sources

Database server	**DatabaseMetaData.getRowIdLifetime**
Db2 for z/OS	ROWID_VALID_TRANSACTION
Db2 on Linux, UNIX, and Windows systems	ROWID_UNSUPPORTED
Db2 for IBM i	ROWID_VALID_FOREVER
IBM Informix	ROWID_VALID_FOREVER

Example: Using PreparedStatement.setRowId with a java.sql.RowId target type: Suppose that rwid is a RowId object. To set parameter 1, use this form of the setRowId method:

```
ps.setRowId(1, rid);
```

Example: Using ResultSet.getRowId to retrieve a ROWID value from a data source: To retrieve a ROWID value from the first column of a result set into RowId object rwid, use this form of the ResultSet.getRowId method:

```
java.sql.RowId rwid = rs.getRowId(1);
```

Example: Using CallableStatement.registerOutParameter with a java.sql.Types.ROWID parameter type: To register parameter 1 of a CALL statement as a java.sql.Types.ROWID data type, use this form of the registerOutParameter method:

```
cs.registerOutParameter(1, java.sql.Types.ROWID)
```

Related reference

"Data types that map to database data types in Java applications" on page 207

To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

Update and retrieval of timestamps with time zone information in JDBC applications

The JDBC methods and data types that you use and the information that the IBM Data Server Driver for JDBC and SQLJ has about the column data types determine the timestamp values that are sent to and received from TIMESTAMP WITH TIME ZONE or TIMESTAMP columns.

Updates of values in TIMESTAMP or TIMESTAMP WITH TIME ZONE columns

You can use the following standard JDBC methods to update a TIMESTAMP WITH TIME ZONE or TIMESTAMP column:

- PreparedStatement.setObject
- PreparedStatement.setTimestamp
- PreparedStatement.setString

For a `PreparedStatement.setTimestamp` call in which the second parameter is a `DBTimestamp` object and the third parameter is a `Calendar` object, the value that is passed to a TIMESTAMP WITH TIME ZONE or TIMESTAMP column contains the time zone value in the `Calendar` parameter, and not the time zone value in the `DBTimestamp` object. For a `PreparedStatement.setTimestamp` in which the second parameter is a `DBTimestamp` object and there is no `Calendar` parameter, the IBM Data Server Driver for JDBC and SQLJ value that is passed to a TIMESTAMP WITH TIME ZONE or TIMESTAMP column has the default time zone, which is that of the Java virtual machine in which the application is running.

If you want the value that is passed to a TIMESTAMP WITH TIME ZONE or TIMESTAMP column to use the time zone that is in the `DBTimestamp` object, you need to use `PreparedStatement.setObject`.

Example: Suppose that table TSTABLE is defined like this:

```
CREATE TABLE TSTABLE (
 TSCOL TIMESTAMP,
 TSTZCOL TIMESTAMP WITH TIME ZONE)
```

Also suppose that the default time zone of the Java Virtual Machine (JVM) is UTC-08:00 (Pacific Standard Time). The following code assigns timestamp values to the column.

```
…
java.util.TimeZone esttz = java.util.TimeZone.getTimeZone("EST");
java.util.Calendar estcal = java.util.Calendar.getInstance(esttz);
                        // Construct a Calendar object with the
                        // UTC-05:00 (Eastern Standard Time) time zone.
java.util.Calendar defcal = java.util.Calendar.getInstance();
                        // Construct a Calendar object
                        // with the default time zone.
java.sql.Timestamp ts =
 java.sql.Timestamp.valueOf("2010-10-27 21:22:33.123456");
                        // Assign a timestamp to a Timestamp object.
DBTimestamp dbts = new DBTimestamp(ts,estcal);
                        // Construct a DBTimestamp object that has
                        // the UTC-05:00 time zone.
…
PreparedStatement ps = con.prepareStatement(
  "INSERT INTO TSTABLE (TSCOL,TSTZCOL) VALUES (?,?)");
//
// Use setTimestamp methods to assign a timestamp value to a
// TIMESTAMP WITH TIME ZONE or TIMESTAMP column
//
ps.setTimestamp(1, ts); // Assign a timestamp value in a Timestamp
                        // object to a TIMESTAMP column.
ps.setTimestamp(2,ts);  // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column.
ps.execute(); // 2010-10-27-21.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type.
              // 2010-10-27-21.22.33.123456-08:00 is assigned to TSCOL
```

```
              // if the driver has no information about the column
              // data type.
              // 2010-10-27-21.22.33.123456-08:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the the column has
              // the TIMESTAMP WITH TIME ZONE data type.
ps.setTimestamp(1, dbts);
                        // Assign a timestamp value in a DBTimestamp
                        // object to a TIMESTAMP column.
ps.setTimestamp(2,dbts);
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column.
ps.execute(); // 2010-10-27-21.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type.
              // 2010-10-27-21.22.33.123456-08:00 is assigned to TSCOL
              // if the driver has no information about the column
              // data type.
              // 2010-02-27-21.22.33.123456-08:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the column has
              // the TIMESTAMP WITH TIME ZONE data type. The
              // default time zone of UTC-08:00 is sent to
              // the column.
ps.setTimestamp(1, ts, estcal);
                        // Assign a timestamp value in a Timestamp
                        // object to a TIMESTAMP column. Include
                        // a Calendar parameter that specifies
                        // the UTC-05:00 time zone.
ps.setTimestamp(2, ts, estcal);
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column. Include
                        // a Calendar parameter that specifies the
                        // UTC-05:00 time zone.
ps.execute(); // 2010-10-28-00.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type.
              // The value is adjusted for the difference
              // between the time zone in the Calendar parameter and
              // the default time zone.
              // 2010-10-28-00.22.33.123456-05:00 is assigned to TSCOL
              // if the driver has no information about the column
              // data type. The value is adjusted for the difference
              // between the time zone in the Calendar parameter and
              // the default time zone.
              // 2010-10-28-00.22.33.123456-05:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the the column has
              // the TIMESTAMP WITH TIME ZONE data type.
              // The value is adjusted for the difference
              // between the time zone in the Calendar parameter and
              // the default time zone.
ps.setTimestamp(1, dbts, estcal);
                        // Assign a timestamp value in a DBTimestamp
                        // object to a TIMESTAMP column. Include
                        // a Calendar parameter that specifies the
                        // UTC-05:00 time zone.
ps.setTimestamp(2, dbts, estcal);
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column.
ps.execute(); // 2010-10-28-00.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type.
              // The value is adjusted for the difference
              // between the time zone in the Calendar parameter and
              // the default time zone.
              // 2010-10-28-00.22.33.123456-05:00 is assigned to TSCOL
              // if the driver has no information about the column
              // data type.
              // The value is adjusted for the difference
              // between the time zone in the Calendar parameter and
              // the default time zone.
              // 2010-10-28-00.22.33.123456-05:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the the column has
              // the TIMESTAMP WITH TIME ZONE data type. The
              // time zone in the Calendar parameter, UTC-05:00,
              // is sent to the column.
              // The value is adjusted for the difference
              // between the time zone in the Calendar parameter and
              // the default time zone.
ps.setTimestamp(1, ts, defcal);
```

```
                        // Assign a timestamp value in a Timestamp
                        // object to a TIMESTAMP column. Include
                        // a Calendar parameter that specifies
                        // the default time zone (UTC-08:00).
ps.setTimestamp(2, ts, defcal);
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column. Include
                        // a Calendar parameter that specifies the
                        // default (UTC-08:00) time zone.
ps.execute(); // 2010-10-27-21.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type.
              // 2010-10-27-21.22.33.123456-08:00 is assigned to TSCOL
              // if the driver has no information about the column
              // data type.
              // 2010-10-27-21.22.33.123456-08:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the the column has
              // the TIMESTAMP WITH TIME ZONE data type.
ps.setTimestamp(1, dbts, defcal);
                        // Assign a timestamp value in a DBTimestamp
                        // object to a TIMESTAMP column
ps.setTimestamp(2, dbts, defcal);
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column
ps.execute(); // 2010-10-27-21.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type
              // 2010-10-27-21.22.33.123456-08:00 is assigned to TSCOL
              // if the driver has no information about the column
              // data type
              // 2010-10-27-21.22.33.123456-08:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the the column has
              // the TIMESTAMP WITH TIME ZONE data type. The
              // default time zone in the Calendar parameter,
              // UTC-08:00, is sent to the column.
//
// Use setObject methods to assign a timestamp value to a
// TIMESTAMP WITH TIME ZONE or TIMESTAMP column
//
ps.setObject(1, ts);    // Assign a timestamp value in a Timestamp
                        // object to a TIMESTAMP column.
ps.setObject(2, ts);
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column.
ps.execute(); // 2010-10-27-21.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type.
              // 2010-10-27-21.22.33.123456-08:00 is assigned to TSCOL
              // if the driver has no information about the column
              // data type. The time zone is the default time zone.
              // 2010-10-27-21.22.33.123456-08:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the the column has
              // the TIMESTAMP WITH TIME ZONE data type. The
              // time zone is the default time zone.
ps.setObject(1, dbts);
                        // Assign a timestamp value in a DBTimestamp
                        // object to a TIMESTAMP column.
ps.setObject(2, dbts);
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column.
ps.execute(); // 2010-10-28-00.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // has the TIMESTAMP data type.
              // 2010-10-28-00.22.33.123456-05:00 is assigned to TSCOL
              // if the driver has no information about the column
              // data type.
              // 2010-10-28-00.22.33.123456-05:00 is assigned
              // to TSTZCOL regardless of whether the driver
              // has information that the the column has
              // the TIMESTAMP WITH TIME ZONE data type.
              // The time zone is the time zone in the DBTimestamp
              // object.
//
// Use setString methods to assign a timestamp value to a
// TIMESTAMP WITH TIME ZONE or TIMESTAMP column
//
ps.setString(1, "2010-10-27-21.22.33.123456");
                        // Assign a constant timestamp value
                        // with no time zone to a TIMESTAMP column.
```

```
ps.setString(2, "2010-10-27-21.22.33.123456");
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column.
ps.execute(); // 2010-10-27-21.22.33.123456 is assigned to TSCOL
              // regardless of whether the driver has information
              // that the column has the TIMESTAMP data type.
              // 2010-10-27-21.22.33.123456-08:00 is assigned
              // to TSTZCOL if the driver has information that
              // the column has the TIMESTAMP WITH TIME ZONE
              // data type. The time zone is the default time zone.
              // 2010-10-27-21.22.33.123456 is assigned to TSTZCOL
              // if the driver has no information about the column
              // data type.
ps.setString(1, "2010-10-27-21.22.33.123456-05:00");
                        // Assign a constant timestamp value
                        // with a time zone to a TIMESTAMP column.
ps.setString(2, "2010-10-27-21.22.33.123456-05:00");
                        // Assign the same timestamp value to
                        // a TIMESTAMP WITH TIME ZONE column.
ps.execute(); // 2010-10-27-21.22.33.123456 is assigned to TSCOL
              // if the driver has information that the column
              // data type is TIMESTAMP.
              // 2010-10-27-21.22.33.123456-05:00 is assigned to
              // TSCOL if the driver has no information about the
              // column data type.
              // 2010-10-27-21.22.33.123456-05:00 is assigned
              // to TSTZCOL regardless of whether the driver has
              // information that the column data type is
              // TIMESTAMP WITH TIME ZONE.
```

Alternatively, if you want to assign data that has a time zone or has a precision of greater than nine to a TIMESTAMP WITH TIME ZONE column, you can construct a `DBTimestamp` object, and use the IBM Data Server Driver for JDBC and SQLJ-only method `DB2PreparedStatement.setDBTimestamp` to update a TIMESTAMP WITH TIME ZONE column.

Example: Suppose that table TSTABLE is defined like this:

```
CREATE TABLE TSTABLE (
 TSCOL TIMESTAMP,
 TSTZCOL TIMESTAMP(12) WITH TIME ZONE)
```

The following code assigns a timestamp value with a time zone and a precision of 10 to each column.

```
…
DBTimestamp tstz =
  DBTimestamp.valueOfDBString("2010-10-28-00.22.33.1234567890-05:00");
                // Create a DBTimestamp object from the input value
PreparedStatement ps = con.prepareStatement(
  "INSERT INTO TSTABLE (TSCOL, TSTXCOL) VALUES (?,?)");

DB2PreparedStatement dbps = (DB2PreparedStatement)ps;
dbps.setDBTimestamp(1, tstz);
dbps.setDBTimestamp(2, tstz);
dbps.execute(); // 2010-10-28-00.22.33.123456 is assigned to TSCOL if
                // the driver has information that the column data type is
                // TIMESTAMP.
                // 2010-10-28-00.22.33.1234567890-05:00 is assigned to TSCOL
                // if the driver has no information about the column
                // data type.
                // 2010-10-28-00.22.33.1234567890-05:00 is assigned to TSTZCOL
                // regardless of whether the driver has information that
                // the column data type is TIMESTAMP(12) WITH TIME ZONE.
```

Retrieval of values from TIMESTAMP or TIMESTAMP WITH TIME ZONE columns

You can use the following standard JDBC methods to retrieve data from a TIMESTAMP WITH TIME ZONE or TIMESTAMP column or output parameter:

- ResultSet.getTimestamp
- CallableStatement.getTimestamp
- ResultSet.getObject
- CallableStatement.getObject

- ResultSet.getString
- CallableStatement.getString

For a `ResultSet.getTimestamp`, `CallableStatement.getTimestamp`, `ResultSet.getObject`, or `CallableStatement.getObject` call, you can specify the type of object that you want the IBM Data Server Driver for JDBC and SQLJ to return by setting the DB2BaseDataSource.timestampOutputType property:

- If you set the property to DB2BaseDataSource.JDBC_TIMESTAMP (1), the driver returns a `java.sql.Timestamp` object.
- If you set the property to DB2BaseDataSource.JCC_DBTIMESTAMP (2), the driver returns a `com.ibm.db2.jcc.DBTimestamp` object.

For a `ResultSet.getTimestamp` or `CallableStatement.getTimestamp` call, if the `ResultSet.getTimestamp` or `CallableStatement.getTimestamp` call has a `Calendar` parameter with a non-null value, the IBM Data Server Driver for JDBC and SQLJ uses the `Calendar` object when it constructs the returned object. If the `ResultSet.getTimestamp` or `CallableStatement.getTimestamp` call has no `Calendar` parameter, or the `Calendar` parameter value is null, the IBM Data Server Driver for JDBC and SQLJ uses the default time zone when it constructs the returned object.

If you want to retrieve a timestamp with the time zone value that is in a TIMESTAMP WITH TIME ZONE column, call `ResultSet.getObject` or `CallableStatement.getObject`, and then call `DBTimestamp.toDBString(true)` to retrieve the timestamp with the time zone.

`getString` retrieves the timestamp value in the standard JDBC format: without the time zone, and with a precision of up to nine. The returned value is adjusted for the difference between the time zone of the column value and the default time zone.

Example: Suppose that table TSTABLE is defined like this:

```
CREATE TABLE TSTABLE (
 TSCOL TIMESTAMP,
 TSTZCOL TIMESTAMP WITH TIME ZONE)
```

Also suppose that the default time zone is UTC-08:00 (Pacific Standard Time). The following code retrieves timestamp values from the TIMESTAMP column.

```
…
java.util.TimeZone esttz = java.util.TimeZone.getTimeZone("EST");
java.util.Calendar estcal = java.util.Calendar.getInstance(esttz);
java.util.Calendar defcal = java.util.Calendar.getInstance();
Statement stmt = conn.createStatement ();
ResultSet rs = stmt.executeQuery("SELECT TSCOL, TSTZCOL FROM TSTABLE");
com.ibm.db2.jcc.DB2ResultSet dbrs = (com.ibm.db2.jcc.DB2ResultSet)rs;
Timestamp ts;
DBTimestamp dbts;
…
rs.next();
// Suppose that the TSCOL column value is 2010-10-27-21.22.33.123456

ts=rs.getTimestamp(1);                // Retrieve the TIMESTAMP column value
                                      // into a Timestamp object.
ts.toString();                        // Format the Timestamp object as a String.
                                      // 2010-10-27-21:22:33.123456 is
                                      // returned.
((DBTimestamp)ts).toDBString(false);  // Cast the retrieved object to a
                                      // DBTimestamp object, and format the
                                      // value as a String, without the time
                                      // zone information.
                                      // 2010-10-27-21.22.33.123456 is returned.
((DBTimestamp)ts).toDBString(true);   // Cast the retrieved object to a
                                      // DBTimestamp object, and format the value
                                      // as a String, with the time zone
                                      // information.
                                      // 2009-02-27-21.22.33.123456-08:00 is
                                      // returned. The time zone is the default
                                      // time zone.
ts=rs.getTimestamp(1,estcal);         // Retrieve the TIMESTAMP column value
                                      // into a Timestamp object. Specify a
```

```
                                    // calendar parameter that says that the
                                    // time zone is UTC-05:00.
ts.toString();                      // Format the value as a String, using the
                                    // default time zone of UTC-08:00.
                                    // 2010-10-27-18:22:33.123456 is
                                    // returned.
((DBTimestamp)ts).toDBString(false);  // Cast the retrieved object to a
                                    // DBTimestamp object, and format the
                                    // value as a String, without the time zone
                                    // information.
                                    // 2010-10-27-21.22.33.123456 is returned.
((DBTimestamp)ts).toDBString(true);   // Cast the retrieved object to a
                                    // DBTimestamp object, and format the
                                    // value as a String, with the time zone
                                    // information.
                                    // 2010-10-27-21.22.33.123456-05:00 is
                                    // returned. The time zone is the time zone
                                    // in the Calendar parameter.
ts=rs.getObject(1);                 // Retrieve the TIMESTAMP column value
                                    // into an Object.
ts.toString();                      // Format the Timestamp object as a String.
                                    // 2010-10-27-21:22:33.123456 is
                                    // returned.
((DBTimestamp)ts).toDBString(false);  // Cast the retrieved object to a
                                    // DBTimestamp object, and format the
                                    // value as a String, without the time
                                    // zone information.
                                    // 2010-10-27-21.22.33.123456 is returned.
((DBTimestamp)ts).toDBString(true);   // Cast the retrieved object to a
                                    // DBTimestamp object, and format the value
                                    // as a String, with the time zone
                                    // information.
                                    // 2009-02-27-21.22.33.123456-08:00 is
                                    // returned. The time zone is the default
                                    // time zone.
```

Alternatively, you can use DB2ResultSet methods to retrieve the TIMESTAMP or TIMESTAMP WITH TIME ZONE column values.

Example: Suppose that table TSTABLE is defined like this:

```
CREATE TABLE TSTABLE (
 TSCOL TIMESTAMP,
 TSTZCOL TIMESTAMP(12) WITH TIME ZONE)
```

Also suppose that the default time zone is UTC-08:00 (Pacific Standard Time). The following code retrieves timestamp values from the TIMESTAMP and TIMESTAMP WITH TIME ZONE columns.

```
…
java.util.TimeZone esttz = java.util.TimeZone.getTimeZone("EST");
java.util.Calendar estcal = java.util.Calendar.getInstance(esttz);
java.util.Calendar defcal = java.util.Calendar.getInstance();
Statement stmt = conn.createStatement ();
ResultSet rs = stmt.executeQuery("SELECT TSCOL, TSTZCOL FROM TSTABLE");
com.ibm.db2.jcc.DB2ResultSet dbrs = (com.ibm.db2.jcc.DB2ResultSet)rs;
Timestamp ts;
DBTimestamp dbts;
…
rs.next();
// Suppose that the TSTZCOL column value is 2010-10-28-00.22.33.123456-05:00, and
// the TSCOL column value is 2010-10-27-21.22.33.123456.
ts=dbrs.getDBTimestamp(1);          // Retrieve the TIMESTAMP column value into
                                    // a Timestamp object.
ts.toString();                      // Format the Timestamp object as a String.
                                    // 2010-10-27-21:22:33.123456 is
                                    // returned.
((DBTimestamp)ts).toDBString(false);  // Format the value as a String, without
                                    // the time zone information.
                                    // 2010-10-27-21.22.33.123456 is returned.
((DBTimestamp)ts).toDBString(true);   // Format the value as a String, with the
                                    // time zone information.
                                    // 2009-02-27-21.22.33.123456-08:00 is
                                    // returned. The time zone is the default
                                    // time zone.
ts=dbrs.getDBTimestamp(2);          // Retrieve the TIMESTAMP WITH TIME ZONE
                                    // column value into a Timestamp object.
ts.toString();                      // Format the Timestamp object as a String.
                                    // 2010-10-27-21:22:33.123456 is
```

```
                                    // returned. The returned value differs
                                    // from the original value because toString
                                    // uses the default time zone in its
                                    // calculations.
((DBTimestamp)ts).toDBString(false);  // Format the value as a String, without
                                    // the time zone information.
                                    // 2010-10-28-00.22.33.123456 is returned.
((DBTimestamp)ts).toDBString(true);   // Format the value as a String, with the
                                    // time zone information.
                                    // 2010-10-28-00.22.33.123456-05:00 is
                                    // returned. The time zone is the time zone
                                    // from the retrieved column value.
dbts = (DBTimestamp)rs.getTimestamp(2);
                                    // Retrieve the TIMESTAMP WITH TIME ZONE
                                    // column value into a DBTimestamp object.
dbts.toString();                    // Format the DBTimestamp object as a String.
                                    // 2010-10-27-21:22:33.123456 is
                                    // returned. The value is adjusted for the
                                    // difference between the time zone in the
                                    // column value and the default time zone.
dbts.toDBString(false);             // Format the value as a String, without
                                    // the time zone information. The value is
                                    // adjusted for the difference between the
                                    // time zone in the column value and the
                                    // default time zone.
                                    // 2010-10-27-21.22.33.123456 is returned.
dbts.toDBString(true);              // Format the value as a String, with the
                                    // time zone information.
                                    // 2009-02-27-21.22.33.123456-08:00 is
                                    // returned. The time zone is the default
                                    // time zone. The value is adjusted for
                                    // the difference between the time zone in
                                    // the column value and the default
                                    // time zone.
dbts = (DBTimestamp)rs.getTimestamp(2, defcal);
                                    // Retrieve the TIMESTAMP WITH TIME ZONE
                                    // column value into a DBTimestamp object,
                                    // using the default Calendar to construct
                                    // the DBTimestamp object.
dbts.toString();                    // Format the DBTimestamp object as a String.
                                    // 2010-10-27-21:22:33.123456 is
                                    // returned. The value is adjusted for
                                    // the difference between the time zone in
                                    // the column value and the time zone
                                    // in the Calendar parameter.
dbts.toDBString(false);             // Format the value as a String, without
                                    // the time zone information.
                                    // 2010-10-27-21.22.33.123456 is returned.
                                    // The value is adjusted for
                                    // the difference between the time zone in
                                    // the column value and the time zone
                                    // in the Calendar parameter.
dbts.toDBString(true);              // Format the value as a String, with the
                                    // time zone information.
                                    // 2009-02-27-21.22.33.123456-08:00 is
                                    // returned.  The value is adjusted for
                                    // the difference between the time zone in
                                    // the column value and the time zone
                                    // in the Calendar parameter.
dbts = (DBTimestamp)rs.getObject(2);  // Retrieve the TIMESTAMP WITH TIME ZONE
                                    // column value into an Object, and cast
                                    // the object as a DBTimestamp object.
dbts.toString();                    // Format the DBTimestamp object as a String.
                                    // 2010-10-27-21:22:33.123456 is
                                    // returned. The returned value differs from
                                    // the original value because toString uses
                                    // the default time zone in its calculations.
dbts.toDBString(false);             // Format the value as a String, without
                                    // the time zone information.
                                    // 2010-10-28-00.22.33.123456 is returned.
dbts.toDBString(true);              // Format the value as a String, with the
                                    // time zone information.
                                    // 2009-10-28-00.22.33.123456-05:00 is
                                    // returned. The time zone is the time
                                    // zone in the retrieved column value.
```

Recommendation: Use `getObject` or `getDBTimestamp`, followed by `setObject` or `setDBTimestamp` when you need to preserve the original timestamp with time zone information when you retrieve data from one table and insert it into another table.

Related reference

"DBTimestamp class" on page 488
The `com.ibm.db2.jcc.DBTimestamp` class can be used to create timestamp objects with a precision of up to picoseconds and time zone information. This class is primarily for support of the SQL TIMESTAMP WITH TIME ZONE data type, which is supported only by Db2 for z/OS.

"Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 servers" on page 253
Some of the IBM Data Server Driver for JDBC and SQLJ properties apply to Db2 data servers only.

Distinct types in JDBC applications

A distinct type is a user-defined data type that is internally represented as a built-in SQL data type. You create a distinct type by executing the SQL statement CREATE DISTINCT TYPE.

In a JDBC program, you can create a distinct type using the `executeUpdate` method to execute the CREATE DISTINCT TYPE statement. You can also use `executeUpdate` to create a table that includes a column of that type. When you retrieve data from a column of that type, or update a column of that type, you use Java identifiers with data types that correspond to the built-in types on which the distinct types are based.

The following example creates a distinct type that is based on an INTEGER type, creates a table with a column of that type, inserts a row into the table, and retrieves the row from the table:

```
Connection con;
Statement stmt;
ResultSet rs;
String empNumVar;
int shoeSizeVar;
…
stmt = con.createStatement();               // Create a Statement object
stmt.executeUpdate(
  "CREATE DISTINCT TYPE SHOESIZE AS INTEGER");
                                            // Create distinct type
stmt.executeUpdate(
  "CREATE TABLE EMP_SHOE (EMPNO CHAR(6), EMP_SHOE_SIZE SHOESIZE)");
                                            // Create table with distinct type
stmt.executeUpdate("INSERT INTO EMP_SHOE " +
  "VALUES ('000010', 6)");                  // Insert a row
rs=stmt.executeQuery("SELECT EMPNO, EMP_SHOE_SIZE FROM EMP_SHOE);
                                            // Create ResultSet for query
while (rs.next()) {
  empNumVar = rs.getString(1);              // Get employee number
  shoeSizeVar = rs.getInt(2);               // Get shoe size (use int
                                            // because underlying type
                                            // of SHOESIZE is INTEGER)
  System.out.println("Employee number = " + empNumVar +
    " Shoe size = " + shoeSizeVar);
}
rs.close();                                 // Close ResultSet
stmt.close();                               // Close Statement
```

Figure 16. Creating and using a distinct type

Related reference

"Data types that map to database data types in Java applications" on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

CREATE TYPE (distinct) (Db2 SQL)

Invocation of stored procedures with ARRAY parameters in JDBC applications

JDBC applications that run under the IBM Data Server Driver for JDBC and SQLJ can call stored procedures that have ARRAY parameters.

ARRAY parameters are supported in stored procedures on Db2 on Linux, UNIX, and Windows systems Version 9.5 and later.

ARRAY parameters are supported in native SQL procedures on Db2 for z/OS Version 11 and later. Programs that call Db2 for z/OS stored procedures with array parameters must use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

You can use `java.sql.Array` objects as arguments for calling stored procedures with array parameters.

For IN or INOUT parameters, use the `Connection.createArrayOf` method to create a `java.sql.Array` object. Use the `CallableStatement.setArray` method or the `CallableStatement.setObject` method to assign a `java.sql.Array` object to an ARRAY stored procedure parameter.

You can register an OUT ARRAY parameter for a stored procedure call by specifying java.sql.Types.ARRAY as the parameter type in a `CallableStatement.registerOutParameter` call.

There are two ways to retrieve data from an ARRAY output parameter:

- Use the `CallableStatement.getArray` method to retrieve the data into a `java.sql.Array` object, and use the `java.sql.Array.getArray` method to retrieve the contents of the `java.sql.Array` object into a Java array.
- Use the `CallableStatement.getArray` method to retrieve the data into a `java.sql.Array` object. Use the `java.sql.Array.getResultSet()` method to retrieve the data into a `ResultSet` object. Use `ResultSet` methods to retrieve elements of the array. Each row of the `ResultSet` contains two columns:
  - An index into the array, which starts at 1
  - The array element

Example: Suppose that input and output parameters IN_PHONE and OUT_PHONE in stored procedure GET_EMP_DATA are arrays that are defined like this:

```
CREATE TYPE PHONENUMBERS AS VARCHAR(10) ARRAY[5]
```

Call GET_EMP_DATA with the two parameters.

```
Connection con;
CallableStatement cstmt;
ResultSet rs;
java.sql.Array inPhoneData;
…
cstmt = con.prepareCall("CALL GET_EMP_DATA(?,?)");
                                        // Create a CallableStatement object
String[] charArray = new String[] {"a", "b", "c"};
inPhoneData = conn.createArrayOf("CHAR", charArray);
cstmt.setArray(1, inPhoneData);         // Set input parameter
cstmt.registerOutParameter (2, java.sql.Types.ARRAY);
                                        // Register out parameters
cstmt.executeUpdate();                  // Call the stored procedure
Array outPhoneData = cstmt.getArray(2);
                                        // Get the output parameter array
System.out.println("Parameter values from GET_EMP_DATA call: ");
String [] outPhoneNums = (String [])outPhoneData.getArray();
                                        // Retrieve output data from the
                                        // JDBC Array object into a Java
                                        // String array
for(int i=0; i<outPhoneNums.length; i++) {
  System.out.print(outPhoneNums[i]);
  System.out.println();
}
```

Savepoints in JDBC applications

An SQL savepoint represents the state of data and schemas at a particular point in time within a unit of work. You can use SQL statements to set a savepoint, release a savepoint, and restore data and schemas to the state that the savepoint represents.

The IBM Data Server Driver for JDBC and SQLJ supports the following methods for using savepoints:

Connection.setSavepoint() or Connection.setSavepoint(String *name*)
Sets a savepoint. These methods return a `Savepoint` object that is used in later `releaseSavepoint` or `rollback` operations.

When you execute either of these methods, the data server executes the form of the SAVEPOINT statement that includes ON ROLLBACK RETAIN CURSORS.

Connection.releaseSavepoint(Savepoint *savepoint*)
Releases the specified savepoint, and all subsequently established savepoints.

Connection.rollback(Savepoint *savepoint*)
Rolls back work to the specified savepoint.

DatabaseMetaData.supportsSavepoints()
Indicates whether a data source supports savepoints.

You can indicate whether savepoints are unique by calling the method `DB2Connection.setSavePointUniqueOption`. If you call this method with a value of `true`, the application cannot set more than one savepoint with the same name within the same unit of recovery. If you call this method with a value of `false` (the default), multiple savepoints with the same name can be created within the same unit of recovery, but creation of a savepoint destroys a previously created savepoint with the same name.

The following example demonstrates how to set a savepoint, roll back to the savepoint, and release the savepoint.

```
Connection con;
Statement stmt;
ResultSet rs;
String empNumVar;
int shoeSizeVar;
…
con.setAutoCommit(false);                    // set autocommit OFF
stmt = con.createStatement();                // Create a Statement object
…                                            // Perform some SQL
con.commit();                                // Commit the transaction
stmt.executeUpdate("INSERT INTO EMP_SHOE " +
  "VALUES ('000010', 6)");                   // Insert a row
((com.ibm.db2.jcc.DB2Connection)con).setSavePointUniqueOption(true);
                                             // Indicate that savepoints
                                             // are unique within a unit
                                             // of recovery
Savepoint savept = con.setSavepoint("savepoint1");
                                             // Create a savepoint
…
stmt.executeUpdate("INSERT INTO EMP_SHOE " +
  "VALUES ('000020', 10)");                  // Insert another row
conn.rollback(savept);                       // Roll back work to the point
                                             //  after the first insert
…
con.releaseSavepoint(savept);                // Release the savepoint
stmt.close();                                // Close the Statement
conn.commit();                               // Commit the transaction
```

Figure 17. Setting, rolling back to, and releasing a savepoint in a JDBC application

Related tasks

“Committing or rolling back JDBC transactions” on page 107
In JDBC, to commit or roll back transactions explicitly, use the `commit` or `rollback` methods.

Related reference

“Data types that map to database data types in Java applications” on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

“Driver support for JDBC APIs” on page 318
The JDBC drivers that are supported by Db2 and IBM Informix database systems have different levels of support for JDBC methods.

“DB2Connection interface” on page 410

The `com.ibm.db2.jcc.DB2Connection` interface extends the `java.sql.Connection` interface.

Retrieval of automatically generated keys in JDBC applications

With the IBM Data Server Driver for JDBC and SQLJ, you can retrieve automatically generated keys (also called auto-generated keys) from a table.

An *automatically generated key* is any value that is generated by the data server, instead of being specified by the user. One type of automatically generated key is the contents of an identity column. An identity column is a table column that provides a way for the data source to automatically generate a numeric value for each row. You define an identity column in a CREATE TABLE or ALTER TABLE statement by specifying the AS IDENTITY clause when you define a column that has an exact numeric type with a scale of 0 (SMALLINT, INTEGER, BIGINT, DECIMAL with a scale of zero, or a distinct type based on one of these types).

For connections to Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems, the IBM Data Server Driver for JDBC and SQLJ supports the return of automatically generated keys for INSERT statements, for searched UPDATE or searched DELETE statements, or for MERGE statements. For UPDATE, DELETE, or MERGE statements, you can identify any columns as automatically generated keys, even if they are not generated by the data server. In this case, the column values that are returned are the column values for the rows that are modified by the UPDATE, DELETE, or MERGE statement.

Restriction: If the `Connection` or `DataSource` property atomicMultiRowInsert is set to `DB2BaseDataSource.YES` (1), you cannot prepare an SQL statement for retrieval of automatically generated keys and use the `PreparedStatement` object for batch updates. The IBM Data Server Driver for JDBC and SQLJ version 3.50 or later throws an `SQLException` when you call the `addBatch` or `executeBatch` method on a `PreparedStatement` object that is prepared to return automatically generated keys.

Related tasks

“Creating and modifying database objects using the Statement.executeUpdate method” on page 30
The `Statement.executeUpdate` is one of the JDBC methods that you can use to update tables and call stored procedures.

“Updating data in tables using the PreparedStatement.executeUpdate method” on page 31
The `Statement.executeUpdate` method works if you update data server tables with constant values. However, updates often need to involve passing values in variables to the tables. To do that, you use the `PreparedStatement.executeUpdate` method.

Retrieving auto-generated keys for an INSERT statement

With the IBM Data Server Driver for JDBC and SQLJ, you can use JDBC methods to retrieve the keys that are automatically generated when you execute an INSERT statement.

Procedure

To retrieve automatically generated keys that are generated by an INSERT statement, you need to perform these steps:

1. Use one of the following methods to indicate that you want to return automatically generated keys:
   - If you plan to use the `PreparedStatement.executeUpdate` method to insert rows, invoke one of these forms of the `Connection.prepareStatement` method to create a `PreparedStatement` object:

     The following form is valid for a table on any data source that supports identity columns.

     Restriction: For IBM Data Server Driver for JDBC and SQLJ version 3.57 or later, the following form is not valid for inserting rows into a view on a Db2 for z/OS data server.

     ```
     Connection.prepareStatement(sql-statement,
       Statement.RETURN_GENERATED_KEYS);
     ```

If the data server is Db2 for z/OS, the following forms are valid only if the data server supports SELECT FROM INSERT statements. With the first form, you specify the names of the columns for which you want automatically generated keys. With the second form, you specify the positions in the table of the columns for which you want automatically generated keys.

```
Connection.prepareStatement(sql-statement, String [] columnNames);
Connection.prepareStatement(sql-statement, int [] columnIndexes);
```

- If you use the `Statement.executeUpdate` method to insert rows, invoke one of these forms of the `Statement.executeUpdate` method:

  The following form is valid for a table on any data source that supports identity columns.

  Restriction: For IBM Data Server Driver for JDBC and SQLJ version 3.57 or later, the following form is not valid for inserting rows into a view on a Db2 for z/OS data server.

  ```
  Statement.executeUpdate(sql-statement, Statement.RETURN_GENERATED_KEYS);
  ```

  If the data server is Db2 for z/OS, the following forms are valid only if the data server supports SELECT FROM INSERT statements. With the first form, you specify the names of the columns for which you want automatically generated keys. With the second form, you specify the positions in the table of the columns for which you want automatically generated keys.

  ```
  Statement.executeUpdate(sql-statement, String [] columnNames);
  Statement.executeUpdate(sql-statement, int [] columnIndexes);
  ```

2. Invoke the `PreparedStatement.getGeneratedKeys` method or the `Statement.getGeneratedKeys` method to retrieve a `ResultSet` object that contains the automatically generated key values.

   If you include the `Statement.RETURN_GENERATED_KEYS` parameter, the data type of the automatically generated keys in the `ResultSet` is DECIMAL, regardless of the data type of the corresponding column.

Example

The following code creates a table with an identity column, inserts a row into the table, and retrieves the automatically generated key value for the identity column. The numbers to the right of selected statements correspond to the previously described steps.

```
import java.sql.*;
import java.math.*;
import com.ibm.db2.jcc.*;

Connection con;
Statement stmt;
ResultSet rs;
java.math.BigDecimal iDColVar;
…
stmt = con.createStatement();         // Create a Statement object

stmt.executeUpdate(
  "CREATE TABLE EMP_PHONE (EMPNO CHAR(6), PHONENO CHAR(4), " +
    "IDENTCOL INTEGER GENERATED ALWAYS AS IDENTITY)");
                                      // Create table with identity column
stmt.executeUpdate("INSERT INTO EMP_PHONE (EMPNO, PHONENO) " +          1
  "VALUES ('000010', '5555')",        // Insert a row
  Statement.RETURN_GENERATED_KEYS);   // Indicate you want automatically
                                      // generated keys
rs = stmt.getGeneratedKeys();         // Retrieve the automatically      2
                                      // generated key value in a ResultSet.
                                      // Only one row is returned.
                                      // Create ResultSet for query
while (rs.next()) {
  java.math.BigDecimal idColVar = rs.getBigDecimal(1);
                                      // Get automatically generated key
                                      // value
  System.out.println("automatically generated key value = " + idColVar);
}
```

```
rs.close();                          // Close ResultSet
stmt.close();                        // Close Statement
```

With any version of the IBM Data Server Driver for JDBC and SQLJ, you can retrieve the most recently assigned value of an identity column by explicitly executing the IDENTITY_VAL_LOCAL built-in function. Execute code similar to this:

```
String idntVal;
Connection con;
Statement stmt;
ResultSet rs;
…
stmt = con.createStatement();     // Create a Statement object
rs = stmt.executeQuery("SELECT IDENTITY_VAL_LOCAL() FROM SYSIBM.SYSDUMMY1");
                                  // Get the result table from the query.
                                  // This is a single row with the most
                                  // recent identity column value.
while (rs.next()) {               // Position the cursor
 idntVal = rs.getString(1);       // Retrieve column value
 System.out.println("Identity column value = " + idntVal);
                                  // Print the column value
}
rs.close();                       // Close the ResultSet
stmt.close();                     // Close the Statement
```

Retrieving auto-generated keys for an UPDATE, DELETE, or MERGE statement

With the IBM Data Server Driver for JDBC and SQLJ, you can use JDBC methods to retrieve the keys that are automatically generated when you execute a searched UPDATE, searched DELETE, or MERGE statement.

Procedure

To retrieve automatically generated keys that are generated by an UPDATE, DELETE, or MERGE statement, you need to perform these steps:

1. Construct a `String` array that contains the names of the columns from which you want to return automatically generated keys.

   The array must be an array of column names, and not column indexes.
2. Set the autocommit mode for the connection to `false`.
3. Use one of the following methods to indicate that you want to return automatically generated keys:
   - If you plan to use the `PreparedStatement.executeUpdate` method to update, delete, or merge rows, invoke this form of the `Connection.prepareStatement` method to create a `PreparedStatement` object:

     ```
     Connection.prepareStatement(sql-statement, String [] columnNames);
     ```
   - If you use the `Statement.executeUpdate` method to update, delete, or merge rows, invoke this form of the `Statement.executeUpdate` method:

     ```
     Statement.executeUpdate(sql-statement, String [] columnNames);
     ```
4. Invoke the `PreparedStatement.getGeneratedKeys` method or the `Statement.getGeneratedKeys` method to retrieve a `ResultSet` object that contains the automatically generated key values.

Example

Suppose that a table is defined like this and has thirty rows:

```
CREATE TABLE EMP_BONUS
  (EMPNO CHAR(6),
   BONUS DECIMAL(9,2))
```

The following code names the EMPNO column as an automatically generated key, updates the thirty rows in the EMP_BONUS table, and retrieves the values of EMPNO for the updated rows. The numbers to the right of selected statements correspond to the previously described steps.

```
import java.sql.*;
…
Connection conn;
…
String[] agkNames = {"EMPNO"};              1
int updateCount = 0;
conn.setAutoCommit(false);                  2
PreparedStatement ps =                      3
 conn.prepareStatement(“UPDATE EMP_BONUS SET BONUS = " +
 “ BONUS + 300.00”,agkNames);
updateCount = ps.executeUpdate();
ResultSet rs = ps.getGeneratedKeys();       4
while (rs.next()) {
 String agkEmpNo = rs.getString(1);
                // Get automatically generated key value
 System.out.println("Automatically generated key value = " + agkEmpNo);
}
ps.close();
conn.close();
```

Named parameter markers in JDBC applications

You can use named parameter markers instead of standard parameter markers in `PreparedStatement` and `CallableStatement` objects to assign values to the input parameter markers. You can also use named parameter markers instead of standard parameter markers in `CallableStatement` objects to register OUT parameters that have named parameter markers.

SQL strings that contain the following SQL elements can include named parameter markers:

- CALL
- DELETE
- INSERT
- MERGE
- PL/SQL block
- SELECT
- SET
- UPDATE

Named parameter markers make your JDBC applications more readable. If you have named parameter markers in an application, set the IBM Data Server Driver for JDBC and SQLJ `Connection` or `DataSource` property enableNamedParameterMarkers to `DB2BaseDataSource.YES` (1) to direct the driver to accept named parameter markers and send them to the data source as standard parameter markers.

Related reference

“Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products” on page 224

Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Using named parameter markers with PreparedStatement objects

You can use named parameter markers instead of standard parameter markers in `PreparedStatement` objects to assign values to the parameter markers.

Before you begin

To ensure that applications with named parameters work correctly, regardless of the data server type and version, before you use named parameter markers in your applications, set the `Connection` or `DataSource` property enableNamedParameterMarkers to `DB2BaseDataSource.YES`.

About this task

Procedure

To use named parameter markers with `PreparedStatement` objects, follow these steps:

1. Execute the `Connection.prepareStatement` method on an SQL statement string that contains named parameter markers.

   The named parameter markers must follow the rules for SQL host variable names.

   You cannot mix named parameter markers and standard parameter markers in the same SQL statement string.

   Named parameter markers are case-insensitive.
2. For each named parameter marker, use a `DB2PreparedStatement.setJccXXXAtName` method to assign a value to each named input parameter.

   If you use the same named parameter marker more than once in the same SQL statement string, you need to call a `setJccXXXAtName` method for that parameter marker only once.

   Recommendation: Do not use the same named parameter marker more than once in the same SQL statement string if the input to that parameter marker is a stream. Doing so can cause unexpected results.

   Restriction: You cannot use standard JDBC `PreparedStatement.setXXX` methods with named parameter markers. Doing so causes an exception to be thrown.
3. Execute the `PreparedStatement`.

Example

The following code uses named parameter markers to update the phone number to '4657' for the employee with employee number '000010'. The numbers to the right of selected statements correspond to the previously described steps.

```
Connection con;
PreparedStatement pstmt;
int numUpd;
…
pstmt = con.prepareStatement(
  "UPDATE EMPLOYEE SET PHONENO=:phonenum WHERE EMPNO=:empnum");
                                // Create a PreparedStatement object     1
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setJccStringAtName
  ("phonenum", "4567");
                                // Assign a value to phonenum parameter  2
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setJccStringAtName
  ("empnum", "000010");
                                // Assign a value to empnum parameter
numUpd = pstmt.executeUpdate();   // Perform the update                  3
pstmt.close();                  // Close the PreparedStatement object
```

The following code uses named parameter markers to update values in a PL/SQL block. The numbers to the right of selected statements correspond to the previously described steps.

```
Connection con;
PreparedStatement pstmt;
int numUpd;
…
String sql =
  "BEGIN " +
  "  UPDATE EMPLOYEE SET PHONENO = :phonenum WHERE EMPNO = :empnum; " +
  "END;";
pstmt = con.prepareStatement(sql); // Create a PreparedStatement object     1
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setJccStringAtName
  ("phonenum", "4567");
                                   // Assign a value to phonenum parameter  2
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setJccStringAtName
  ("empnum", "000010");
                                   // Assign a value to empnum parameter
numUpd = pstmt.executeUpdate();    // Perform the update                    3
pstmt.close();                     // Close the PreparedStatement object
```

Related reference

“DB2PreparedStatement interface” on page 448
The `com.ibm.db2.jcc.DB2PreparedStatement` interface extends the `com.ibm.db2.jcc.DB2Statement` and `java.sql.PreparedStatement` interfaces.

Using named parameter markers with CallableStatement objects

You can use named parameter markers instead of standard parameter markers in `CallableStatement` objects to assign values to IN or INOUT parameters and to register OUT parameters.

Before you begin

To ensure that applications with named parameters work correctly, regardless of the data server type and version, before you use named parameter markers in your applications, set the `Connection` or `DataSource` property enableNamedParameterMarkers to `DB2BaseDataSource.YES`.

About this task

Procedure

To use named parameter markers with `CallableStatement` objects, follow these steps:

1. Execute the `Connection.prepareCall` method on an SQL statement string that contains named parameter markers.

   The named parameter markers must follow the rules for SQL host variable names.

   You cannot mix named parameter markers and standard parameter markers in the same SQL statement string.

   Named parameter markers are case-insensitive.
2. If you do not know the names of the named parameter markers in the CALL statement, or the mode of the parameters (IN, OUT, or INOUT):
   a) Call the `CallableStatement.getParameterMetaData` method to obtain a `ParameterMetaData` object with information about the parameters.
   b) Call the `ParameterMetaData.getParameterMode` method to retrieve the parameter mode.
   c) Cast the `ParameterMetaData` object to a `DB2ParameterMetaData` object.
   d) Call the `DB2ParameterMetaData.getParameterMarkerNames` method to retrieve the parameter names.
3. For each named parameter marker that represents an OUT parameter, use a `DB2CallableStatement.registerJccOutParameterAtName` method to register the OUT parameter with a data type.

If you use the same named parameter marker more than once in the same SQL statement string, you need to call a `registerJccOutParameterAtName` method for that parameter marker only once. All parameters with the same name are registered as the same data type.

Restriction: You cannot use standard JDBC `CallableStatement.registerOutParameter` methods with named parameter markers. Doing so causes an exception to be thrown.

4. For each named parameter marker for an input parameter, use a `DB2CallableStatement.setJccXXXAtName` method to assign a value to each named input parameter.

   `setJccXXXAtName` methods are inherited from `DB2PreparedStatement`.

   If you use the same named parameter marker more than once in the same SQL statement string, you need to call a `setJccXXXAtName` method for that parameter marker only once.

   Recommendation: Do not use the same named parameter marker more than once in the same SQL statement string if the input to that parameter marker is a stream. Doing so can cause unexpected results.
5. Execute the `CallableStatement`.
6. Call `CallableStatement.getXXX` methods or `DB2CallableStatement.getJccXXXAtName` methods to retrieve output parameter values.

Example

The following code illustrates calling a stored procedure that has one input VARCHAR parameter and one output INTEGER parameter, which are represented by named parameter markers. The numbers to the right of selected statements correspond to the previously described steps.

```
…
CallableStatement cstmt =
  con.prepareCall("CALL MYSP(:inparm,:outparm)");
                                    // Create a CallableStatement object  1
((com.ibm.db2.jcc.DB2CallableStatement)cstmt).
   registerJccOutParameterAtName("outparm", java.sql.Types.INTEGER);
                                    // Register OUT parameter data type   3
((com.ibm.db2.jcc.DB2CallableStatement)cstmt).setJccStringAtName("inparm", "4567");
                                  // Assign a value to inparm parameter    4

cstmt.executeUpdate();            // Call the stored procedure             5
int outssid = cstmt.getInt(2);    // Get the output parameter value        6
cstmt.close();
```

Related reference

“DB2CallableStatement interface” on page 402
The `com.ibm.db2.jcc.DB2CallableStatement` interface extends the `java.sql.CallableStatement` and the `com.ibm.db2.jcc.DB2PreparedStatement` interfaces.

“DB2PreparedStatement interface” on page 448
The `com.ibm.db2.jcc.DB2PreparedStatement` interface extends the `com.ibm.db2.jcc.DB2Statement` and `java.sql.PreparedStatement` interfaces.

Retrieving JSON documents from a ResultSet

You can query a relational table, and then convert the `ResultSet` that you retrieve to a `com.ibm.db2.jcc.json.DB2JSONResultSet` object, which holds the data in JSON format. After you create the `DB2JSONResultSet` object, you can use methods on that object to retrieve the JSON documents or JSON snippets.

Procedure

To retrieve JSON documents or snippets from `ResultSet` objects, follow this procedure.

1. Execute a query against a relational table whose data you want to convert to JSON format. Retrieve the contents of the table into a `ResultSet` object.

2. Create a DB2JSONResultSet object from the ResultSet object in one of the following ways:
   - For a stand-alone application, cast the ResultSet object to a DB2ResultSet object, and execute the DB2ResultSet.toJSONResultSet method to obtain a DB2JSONResultSet object. For example:

     ```
     DB2JSONResultSet jsonrs = ((DB2ResultSet) rs).toJSONResultSet();
     ```

   - For a web application, unwrap the ResultSet object to a DB2ResultSet object. Then execute the DB2ResultSet.toJSONResultSet method to obtain a DB2JSONResultSet object. For example:

     ```
     DB2ResultSet db2rs = rs.unwrap ( DB2ResultSet.class);
     DB2JSONResultSet jsonrs = db2rs.toJSONResultSet();
     ```

   The data type mappings for conversion of the columns in the ResultSet object to the fields in the DB2JSONResultSet object are as follows:

Db2 data type of a ResultSet column	JSON data type of a DB2JSONResultSet field
BIGINT DECIMAL DOUBLE FLOAT NUMERIC SMALLINT	Number
CHAR VARCHAR	String

   Restrictions:

   - After you obtain the DB2JSONResultSet object, you can no longer retrieve data directly from the ResultSet object.
   - You cannot create a DB2JSONResultSet object if the ResultSet object contains columns of the BLOB, CLOB, XML, VARBINARY, or BINARY data types.

3. Use the appropriate DB2JSONResultSet method to retrieve the data from the DB2JSONResultSet object.

Method name	Function of the method
getAsciiStream	Returns the contents of the DB2JSONResultSet object as a java.io.InputStream object
getCharacterStream	Returns a java.io.Reader object on which applications can call methods to read the JSON document incrementally
getCurrentRow	Returns the current row of the DB2JSONResultSet as a JSON snippet
next	Moves the cursor to the next row in the DB2JSONResultSet object
toJSONString	Returns the rest of the DB2JSONResultSet object, starting with the current row, as a String

4. Close the DB2JSONResultSet object.

Examples

The numbers to the right of statements in the following examples correspond to the previously described steps.

Example: Use DB2JSONResultSet.getCurrentRow to retrieve one row of a JSON document at a time.

```
sql = "SELECT EMPNO, SALARY FROM EMPLOYEE";
ResultSet rs =
 stmt.executeQuery(sql);                                          1
                                        // ResultSet contains a CHAR
                                        // and a DECIMAL column
DB2JSONResultSet jsonrs = ((DB2ResultSet) rs).toJSONResultSet();  2
                                        // DB2JSONResultSet contains
                                        // String and Number fields
while(jsonrs.next()) {
 String row = json.getCurrentRow();                               3
 …
 // Process row
}
jsonrs.close();                         // Close the DB2JSONResultSet 4
```

Example: Use DB2JSON.toJSONString to retrieve an entire JSON document into a String.

```
sql = "SELECT EMPNO, PHONENO FROM EMPLOYEE";
ResultSet rs =
 stmt.executeQuery(sql);                                          1
                                         // ResultSet contains a CHAR
                                         // and a DECIMAL column
DB2JSONResultSet jsonrs = ((DB2ResultSet) rs).toJSONResultSet();  2
                                         // DB2JSONResultSet contains
                                         // String and Number fields
String jsondoc = json.toJSONString();                             3
 …
// Process contents of string
jsonrs.close();                         // Close the DB2JSONResultSet 4
```

Example: Use DB2JSONResultSet.getAsciiStream to read the JSON document into an AsciiStream.

```
sql = "SELECT EMPNO, PHONENO FROM EMPLOYEE";
ResultSet rs =
 stmt.executeQuery(sql);                                          1
                                        // ResultSet contains a CHAR
                                        // and a DECIMAL column
DB2JSONResultSet jsonrs = ((DB2ResultSet) rs).toJSONResultSet();  2
                                        // DB2JSONResultSet contains
                                        // String and Number fields
InputStream is = jsonrs.getAsciiStream();                         3
char  [] buff = new char [1024];
int  b = 0;
do  {                                   // Read and print AsciiStream contents
 b = is.read ();
 if  (b > 0) {
  System.out.print ((char)b);
 }
} while (b > 0);
is.close();
jsonrs.close();                         // Close the DB2JSONResultSet 4
```

Example: Use DB2JSONResultSet.getCharacterStream to retrieve an entire JSON document into a character stream. Then read the document contents into a buffer and print them.

```
sql = "SELECT EMPNO, PHONENO FROM EMPLOYEE";
ResultSet rs =
 stmt.executeQuery(sql);                                          1
                                        // ResultSet contains a CHAR
                                        // and a DECIMAL column
DB2JSONResultSet jsonrs = ((DB2ResultSet) rs).toJSONResultSet();  2
                                        // DB2JSONResultSet contains
                                        // String and Number fields
Stream reader = jsonrs.getCharacterStream ();                     3
char [] buff = new char[1024];
int len = 0;
do {                                    // Read and print CharacterStream contents
 len = reader.read(buff);
 if (len > 0) {
  System.out.println(String.copyValueOf(buff,0,len));
 }
}
```

```
reader.close();
jsonrs.close();                          // Close the DB2JSONResultSet 4
```

Providing extended client information to the data source with IBM Data Server Driver for JDBC and SQLJ-only methods

A set of IBM Data Server Driver for JDBC and SQLJ-only methods provide extra information about the client to the server. This information can be used for accounting, workload management, or debugging.

About this task

Extended client information is sent to the database server when the application performs an action that accesses the server, such as executing SQL.

In the IBM Data Server Driver for JDBC and SQLJ version 4.0 or later, the IBM Data Server Driver for JDBC and SQLJ-only methods are deprecated. You should use `java.sql.Connection.setClientInfo` instead.

The IBM Data Server Driver for JDBC and SQLJ-only methods are listed in the following table.

Table 13. Methods that provide client information to the data server

Method	Information provided
setDB2ClientAccountingInformation	Accounting information
setDB2ClientApplicationInformation	Name of the application that is working with a connection
setDB2ClientDebugInfo	The CLIENT DEBUGINFO connection attribute for the Unified debugger
setDB2ClientProgramId	A caller-specified string that helps the caller identify which program is associated with a particular SQL statement. setDB2ClientProgramId does not apply to Db2 on Linux, UNIX, and Windows systems data servers.
setDB2ClientUser	User name for a connection
setDB2ClientWorkstation	Client workstation name for a connection

Procedure

To set the extended client information, follow these steps:

1. Create a `Connection`.
2. Cast the `java.sql.Connection` object to a `com.ibm.db2.jcc.DB2Connection`.
3. Call any of the methods shown in Table 13 on page 82.
4. Execute an SQL statement to cause the information to be sent to the data server.

Example

The following code performs the previous steps to pass a user name and a workstation name to the data server. The numbers to the right of selected statements correspond to the previously-described steps.

```
public class ClientInfoTest {
  public static void main(String[] args) {
    String url = "jdbc:db2://sysmvs1.stl.ibm.com:5021/san_jose";
    try {
      Class.forName("com.ibm.db2.jcc.DB2Driver");
      String user = "db2adm";
      String password = "db2adm";
      Connection conn = DriverManager.getConnection(url,        1
        user, password);
      if (conn instanceof DB2Connection) {
        DB2Connection db2conn = (DB2Connection) conn;           2
        db2conn.setDB2ClientUser("Michael L Thompson");         3
        db2conn.setDB2ClientWorkstation("sjwkstn1");
        // Execute SQL to force extended client information to be sent
        // to the server
        conn.prepareStatement("SELECT * FROM SYSIBM.SYSDUMMY1"
          + "WHERE 0 = 1").executeQuery();                      4
      }
    } catch (Throwable e) {
        e.printStackTrace();
      }
  }
}
```

Figure 18. Example of passing extended client information to a data server

Related reference

“IBM Data Server Driver for JDBC and SQLJ extensions to JDBC” on page 388
The IBM Data Server Driver for JDBC and SQLJ provides a set of extensions to the support that is provided by the JDBC specification.

Providing extended client information to the data source with client info properties

The IBM Data Server Driver for JDBC and SQLJ version 4.0 supports JDBC 4.0 client info properties, which you can use to provide extra information about the client to the server. This information can be used for accounting, workload management, or debugging.

About this task

Extended client information is sent to the database server when the application performs an action that accesses the server, such as executing SQL.

The application can also use the `Connection.getClientInfo` method to retrieve client information from the database server, or execute the `DatabaseMetaData.getClientInfoProperties` method to determine which client information the driver supports.

The JDBC 4.0 client info properties should be used instead IBM Data Server Driver for JDBC and SQLJ-only methods, which are deprecated.

Procedure

To set client info properties, follow these steps:

1. Create a `Connection`.
2. Call the `java.sql.Connection.setClientInfo` method to set any of the client info properties that the database server supports.
3. Execute an SQL statement to cause the information to be sent to the database server.

Example

The following code performs the previous steps to pass a client's user name and host name to the data server. The numbers to the right of selected statements correspond to the previously-described steps.

```
public class ClientInfoTest {
  public static void main(String[] args) {
   String url = "jdbc:db2://sysmvs1.stl.ibm.com:5021/san_jose";
    try {
      Class.forName("com.ibm.db2.jcc.DB2Driver");
      String user = "db2adm";
      String password = "db2adm";
      Connection conn = DriverManager.getConnection(url,       1
        user, password);
      conn.setClientInfo("ClientUser", "Michael L Thompson"); 2
      conn.setClientInfo("ClientHostname", "sjwkstn1");
      // Execute SQL to force extended client information to be sent
      // to the server
      conn.prepareStatement("SELECT * FROM SYSIBM.SYSDUMMY1"
         + "WHERE 0 = 1").executeQuery();                     3
    } catch (Throwable e) {
      e.printStackTrace();
    }
  }
}
```

Figure 19. Example of passing extended client information to a data server

Client info properties support by the IBM Data Server Driver for JDBC and SQLJ

JDBC 4.0 includes client info properties, which contain information about a connection to a data source. The `DatabaseMetaData.getClientInfoProperties` method returns a list of client info properties that the IBM Data Server Driver for JDBC and SQLJ supports.

When you call `DatabaseMetaData.getClientInfoProperties`, a result set is returned that contains the following columns:

- NAME
- MAX_LEN
- DEFAULT_VALUE
- DESCRIPTION

The following table lists the client info property values that the IBM Data Server Driver for JDBC and SQLJ returns for Db2 on Linux, UNIX, and Windows systems and for Db2 for IBM i.

Table 14. Client info property values for Db2 on Linux, UNIX, and Windows systems and for Db2 for IBM i

NAME	MAX_LEN (bytes)	DEFAULT_VALUE	DESCRIPTION
clientAccountingInformation	255	Empty string	The value of the accounting string from the client information that is specified for the connection. This value is stored in Db2 special register CURRENT CLIENT_ACCTNG.
clientApplicationInformation	255	Empty string	The name of the application that is currently using the connection. This value is stored in Db2 special register CURRENT CLIENT_APPLNAME.
clientUser	255	Empty string	The name of the user on whose behalf the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_USERID.

Table 14. Client info property values for Db2 on Linux, UNIX, and Windows systems and for Db2 for IBM i (continued)

NAME	MAX_LEN (bytes)	DEFAULT_VALUE	DESCRIPTION
clientWorkstation	255	The host name of the local host. Starting with version 3.68 or 4.18 of the IBM Data Server Driver for JDBC and SQLJ, if clientWorkstation is set to 'NODEFAULT', no value is sent to the data server.	The host name of the computer on which the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_WRKSTNNAME.

The following table lists the client info property values that the IBM Data Server Driver for JDBC and SQLJ returns for Db2 for z/OS when the connection uses type 4 connectivity.

Table 15. Client info property values for type 4 connectivity to Db2 for z/OS

NAME	MAX_LEN (bytes)	DEFAULT_VALUE	DESCRIPTION
clientAccountingInformation	255	A string of the form JCC*version**client-ip*, where *version* is the driver version, and *client-ip* is the IP address of the client.	The value of the accounting string from the client information that is specified for the connection. This value is stored in Db2 special register CURRENT CLIENT_ACCTNG.
clientApplicationInformation	255	The string "db2jcc_application".	The name of the application that is currently using the connection. This value is stored in Db2 special register CURRENT CLIENT_APPLNAME.[1]
clientCorrelationToken	255	An LUWID (logical unit of work ID) that the data server generates.	A unique value that allows you to correlate your business processes across the enterprise. This value is stored in Db2 special register CURRENT CLIENT_CORR_TOKEN. The client correlation token value is available in the accounting correlation header record of a Db2 trace, and in the -DISPLAY THREAD command output.
clientUser	128	The user ID that was specified when the connection was established.	The name of the user on whose behalf the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_USERID.[2]
clientWorkstation	255	The string "db2jcc_local". For version 3.68 or 4.18, or later of the IBM Data Server Driver for JDBC and SQLJ, if clientWorkstation is set to 'NODEFAULT', no value is sent to the data server.	The host name of the computer on which the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_WRKSTNNAME.

Notes:

1. Db2 for z/OS traces for IFCID 411, which collect statistics for application names, are limited to 6000 unique application names. If this limit is exceeded, the Db2 data server issues error DSNL030I with reason code 00D3105D, and stops collecting statistics for any new application names until the distributed data facility (DDF) is restarted.
2. Db2 for z/OS traces for IFCID 412, which collect statistics for user IDs, are limited to 6000 unique user IDs. If this limit is exceeded, the Db2 data server issues error DSNL030I with reason code 00D3105E, and stops collecting statistics for any new user IDs until the distributed data facility (DDF) is restarted.

The following table lists the client info property values that the IBM Data Server Driver for JDBC and SQLJ returns for Db2 for z/OS when the connection uses type 2 connectivity.

Table 16. Client info property values for type 2 connectivity on Db2 for z/OS

NAME	MAX_LEN (bytes)	DEFAULT_VALUE	DESCRIPTION
clientAccountingInformation	255	Empty string.	The value of the accounting string from the client information that is specified for the connection. This value is stored in Db2 special register CURRENT CLIENT_ACCTNG.
clientApplicationInformation	255	The string "db2jcc_application".	The name of the application that is currently using the connection. This value is stored in Db2 special register CURRENT CLIENT_APPLNAME.[1]
clientCorrelationToken	255	An LUWID (Logical Unit of Work ID) that the data server generates.	A unique value that allows you to correlate your business processes across the enterprise. This value is stored in Db2 special register CURRENT CLIENT_CORR_TOKEN. The client correlation token value is available in the accounting correlation header record of a Db2 trace, and in the -DISPLAY THREAD command output.
clientUser	128	The user ID that was specified for the connection. If no user ID was specified, the RACF user ID is used.	The name of the user on whose behalf the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_USERID.[2]
clientWorkstation	255	The string "RRSAF". For version 3.68 or 4.18, or later of the IBM Data Server Driver for JDBC and SQLJ, if clientWorkstation is set to 'NODEFAULT', no value is sent to the data server.	The host name of the computer on which the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_WRKSTNNAME.

Notes:

1. Db2 for z/OS traces for IFCID 411 that monitor application names are limited to 6000 unique application names. If this limit is exceeded, the Db2 data server issues error DSNL030I with reason code 00D3105D, and stops collecting statistics for any new application names until the distributed data facility (DDF) is restarted.
2. Db2 for z/OS traces for IFCID 412 that monitor user IDs are limited to 6000 unique user IDs. If this limit is exceeded, the Db2 data server issues error DSNL030I with reason code 00D3105E, and stops collecting statistics for any new user IDs until the distributed data facility (DDF) is restarted.

The following table lists the client info property values that the IBM Data Server Driver for JDBC and SQLJ returns for IBM Informix

Table 17. Client info property values for IBM Informix

NAME	MAX_LEN (bytes)	DEFAULT_VALUE	DESCRIPTION
clientAccountingInformation	199	Empty string	The value of the accounting string from the client information that is specified for the connection.
clientApplicationInformation	20	Empty string	The name of the application that is currently using the connection.
clientUser	1024	Empty string	The name of the user on whose behalf the application that is using the connection is running.

Table 17. Client info property values for IBM Informix (continued)

NAME	MAX_LEN (bytes)	DEFAULT_VALUE	DESCRIPTION
clientWorkstation	20	The host name of the local host. For versions of the IBM Data Server Driver for JDBC and SQLJ starting with 4.18 or 3.68, if clientWorkstation is set to 'NODEFAULT', no value is sent to the data server.	The host name of the computer on which the application that is using the connection is running.

Extended parameter information with the IBM Data Server Driver for JDBC and SQLJ

IBM Data Server Driver for JDBC and SQLJ-only methods and constants let you assign the default value or no value to table columns or `ResultSet` columns.

The data server must support extended indicators before you can use the methods that provide extended indicator information in your Java applications. If you call one of those methods against a data server that does not support extended indicators, an exception is thrown. Extended parameter information is supported by Db2 for z/OS Version 10 or later, or Db2 on Linux, UNIX, and Windows systems Version 9.7 or later.

The methods that provide extended parameter information are listed in the following table.

Extended parameter information methods	Purpose
`DB2PreparedStatement.setDBDefault`, `DB2PreparedStatement.setJccDBDefaultAtName`	Sets an input parameter to its default value.
`DB2PreparedStatement.setDBUnassigned`, `DB2PreparedStatement.setJccDBUnassignedAtName`	Indicates that an input parameter is unassigned. This action yields the same behavior that would occur if the input parameter did not appear in the SQL statement text.
`DB2ResultSet.updateDBDefault`	Sets a column value in the current `ResultSet` row to its default value.

These methods are applicable only for parameter markers that appear in one of the following places:

- The SET list of an UPDATE statement
- The SET list of a MERGE statement
- The VALUES list of an INSERT statement
- The VALUES list of a MERGE statement
- The source table in a MERGE statement
- The SELECT list of an INSERT from SELECT statement

An `SQLException` is raised if you use these methods in any other context.

Alternatively, you can use the standard `PreparedStatement.setObject` or `ResultSet.updateObject` methods with IBM Data Server Driver for JDBC and SQLJ-only constants `DB2PreparedStatement.DB_PARAMETER_DEFAULT` or `DB2PreparedStatement.DB_PARAMETER_UNASSIGNED` to assign the default value or no value to parameters.

Extended parameter information can simplify application programs that have several input variables, each of which can send a value or the default value to the data server, or does not need to appear in the SQL statement. Instead of preparing separate statement strings for all combinations of variable values, you can prepare a single statement string. The resulting `PreparedStatement` object can be used in

a homogeneous batch, whereas multiple different PreparedStatement objects cannot be used in a homogeneous batch.

Related reference

"DB2PreparedStatement interface" on page 448
The com.ibm.db2.jcc.DB2PreparedStatement interface extends the com.ibm.db2.jcc.DB2Statement and java.sql.PreparedStatement interfaces.

Using DB2PreparedStatement methods or constants to provide extended parameter information

Use DB2PreparedStatement methods or PreparedStatement methods with DB2PreparedStatement constants to assign default values to target columns or to assign no values to target columns.

About this task

Follow these steps to send extended client information for a PreparedStatement to the data server.

Procedure

1. Create a PreparedStatement object.

   The SQL statement is a INSERT, UPDATE, or MERGE statement.
2. If you are not using setObject to assign the values, cast the PreparedStatement object to a com.ibm.db2.jcc.DB2PreparedStatement object.
3. Call one of the following methods:
   - If you are not using setObject to assign the value:
     - To assign the default value of the target column to the input parameter, call DB2PreparedStatement.setDBDefault or DB2PreparedStatement.setJccDBDefaultAtName.
     - To mark the input parameter as unassigned, call DB2PreparedStatement.setDBUnassigned or DB2PreparedStatement.setJccDBUnassignedAtName.
   - If you are using setObject to assign the value:
     - To assign the default value of the target column to the input parameter, call PreparedStatement.setObject with DB2PreparedStatement.DB_PARAMETER_DEFAULT as the assigned value.
     - To mark the input parameter as unassigned, call PreparedStatement.setObject with DB2PreparedStatement.DB_PARAMETER_UNASSIGNED as the assigned value.
4. Execute the SQL statement.

Example

The following code assigns the default values of the target columns to the third and fifth parameters in an INSERT statement. The numbers to the right of selected statements correspond to the previously described steps.

```
import java.sql.*;
import com.ibm.db2.jcc.*;

Connection conn;
…
PreparedStatement p = conn.prepareStatement(                  1
  "INSERT INTO DEPARTMENT " +
  "(DEPTNO, DEPTNAME, MGRNO, ADMRDEPT, LOCATION) " +
  "VALUES (?,?,?,?,?)");
p.setString(1, "X00");
p.setString(2, "FACILITIES");
p.setString(4, "A00");
((com.ibm.db2.jcc.DB2PreparedStatement)p).setDBDefault(3);    2,3
```

```
((com.ibm.db2.jcc.DB2PreparedStatement)p).setDBDefault(5);
int uCount = p.executeUpdate();                                    4
…
p.close();                          // Close PreparedStatement
```

The following code uses the PreparedStatement.setObject method and DB2PreparedStatement constants to perform the same function as in the previous example. The numbers to the right of selected statements correspond to the previously described steps.

```
import java.sql.*;
import com.ibm.db2.jcc.*;

Connection conn;
…

PreparedStatement p = conn.prepareStatement(                       1
  "INSERT INTO DEPARTMENT " +
  "(DEPTNO, DEPTNAME, MGRNO, ADMRDEPT, LOCATION) " +
  "VALUES (?,?,?,?,?)");
p.setString(1, "X00");
p.setString(2, "FACILITIES");
p.setString(4, "A00");
p.setObject(3, DB2PreparedStatement.DB_PARAMETER_DEFAULT);         3
p.setObject(5, DB2PreparedStatement.DB_PARAMETER_DEFAULT);
int uCount = p.executeUpdate();                                    4
…
p.close();                          // Close PreparedStatement
```

In these examples, use of the method DB2PreparedStatement.setDBDefault or the constant DB2PreparedStatement.DB_PARAMETER_DEFAULT simplifies programming of the INSERT operation. If DB2PreparedStatement.setDBDefault or DB2PreparedStatement.DB_PARAMETER_DEFAULT is not used, up to 32 different PreparedStatement objects are necessary to cover all combinations of default and non-default input values.

Using DB2ResultSet methods or DB2PreparedStatement constants to provide extended parameter information

Use DB2ResultSet methods or ResultSet methods with DB2PreparedStatement constants to assign default values to target columns in a DB2ResultSet.

About this task

Follow these steps to update a ResultSet with extended client information.

Procedure

1. Create a PreparedStatement object.

   The SQL statement is a SELECT statement.
2. Invoke PreparedStatement.setXXX methods to pass values to any input parameters.
3. Invoke the PreparedStatement.executeQuery method to obtain the result table from the SELECT statement in a ResultSet object.
4. Position the cursor to the row that you want to update or insert.
5. Update columns in the ResultSet row.
   - If you are not using updateObject to update a value:
     - To assign the default value to the target column of the ResultSet, cast the ResultSet to a DB2ResultSet, and call DB2ResultSet.updateDBDefault.
   - If you are using updateObject to assign the value:
     - To assign the default value to the target column of the ResultSet, call ResultSet.updateObject with DB2PreparedStatement.DB_PARAMETER_DEFAULT as the assigned value.

6. Execute `ResultSet.updateRow` if you are updating an existing row, or `ResultSet.insertRow` if you are inserting a new row.

Example

The following code inserts a row into a `ResultSet` with the default value in the second column, and does not modify the value in the first column. The numbers to the right of selected statements correspond to the previously described steps.

```
import java.sql.*;
import com.ibm.db2.jcc.*;

Connection conn;
…
PreparedStatement p = conn.prepareStatement (          1
  "SELECT MGRNO, LOCATION " +
  "FROM DEPARTMENT");
ResultSet rs = p.executeQuery ();                      3
rs.next ();
rs.moveToInsertRow();                                  4
((DB2ResultSet)rs).updateDBDefault (2);                5
rs.insertRow();                                        6
…
rs.close();                           // Close ResultSet
p.close();                            // Close PreparedStatement
```

The following code uses the `ResultSet` interface with `DB2PreparedStatement` constants to perform the same function as in the previous example. The numbers to the right of selected statements correspond to the previously described steps.

```
import java.sql.*;
import com.ibm.db2.jcc.*;

Connection conn;
…
PreparedStatement p = conn.prepareStatement (          1
  "SELECT MGRNO, LOCATION " +
  "FROM DEPARTMENT");
ResultSet rs = p.executeQuery ();                      3
rs.next ();
rs.moveToInsertRow();                                  4
rs.updateObject (2,                                    5
 DB2PreparedStatement.DB_PARAMETER_DEFAULT);
rs.insertRow();                                        6
…
rs.close();                           // Close ResultSet
p.close();                            // Close PreparedStatement
```

XML data in JDBC applications

In JDBC applications, you can store data in XML columns and retrieve data from XML columns.

In database tables, the XML built-in data type is used to store XML data in a column as a structured set of nodes in a tree format.

JDBC applications can send XML data to the data server or retrieve XML data from the data server in one of the following forms:

- As textual XML data
- As binary XML data, if the data server supports it

In JDBC applications, you can:

- Store an entire XML document in an XML column using `setXXX` methods.
- Retrieve an entire XML document from an XML column using `getXXX` methods.
- Retrieve a sequence from a document in an XML column by using the SQL XMLQUERY function to retrieve the sequence into a serialized sequence in the database, and then using `getXXX` methods to retrieve the data into an application variable.

- Retrieve a sequence from a document in an XML column as a user-defined table by using the SQL XMLTABLE function to define the result table and retrieve it. Then use `getXXX` methods to retrieve the data from the result table into application variables.

JDBC 4.0 `java.sql.SQLXML` objects can be used to retrieve and update data in XML columns. Invocations of metadata methods, such as `ResultSetMetaData.getColumnTypeName` return the integer value `java.sql.Types.SQLXML` for an XML column type.

Related concepts

"XML data retrieval in JDBC applications" on page 93
In JDBC applications, you use `ResultSet.getXXX` or `ResultSet.getObject` methods to retrieve data from XML columns.

"XML column updates in JDBC applications" on page 91
In a JDBC application, you can update or insert data into XML columns of a table at a Db2 data server using XML textual data. You can update or insert data into XML columns of a table using binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports binary XML data.

Related reference

"Data types that map to database data types in Java applications" on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

XML column updates in JDBC applications

In a JDBC application, you can update or insert data into XML columns of a table at a Db2 data server using XML textual data. You can update or insert data into XML columns of a table using binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports binary XML data.

The following table lists the methods and corresponding input data types that you can use to put data in XML columns.

Table 18. Methods and data types for updating XML columns

Method	Input data type
PreparedStatement.setAsciiStream	InputStream
PreparedStatement.setBinaryStream	InputStream
PreparedStatement.setBlob	Blob
PreparedStatement.setBytes	byte[]
PreparedStatement.setCharacterStream	Reader
PreparedStatement.setClob	Clob
PreparedStatement.setObject	byte[], Blob, Clob, SQLXML, DB2Xml (deprecated), InputStream, Reader, String
PreparedStatement.setSQLXML"1" on page 91	SQLXML
PreparedStatement.setString	String

Note:

1. This method requires JDBC 4.0 or later.

The encoding of XML data can be derived from the data itself, which is known as *internally encoded* data, or from external sources, which is known as *externally encoded* data. XML data that is sent to the

database server as binary data is treated as internally encoded data. XML data that is sent to the data source as character data is treated as externally encoded data.

External encoding for Java applications is always Unicode encoding.

Externally encoded data can have internal encoding. That is, the data might be sent to the data source as character data, but the data contains encoding information. The data source handles incompatibilities between internal and external encoding as follows:

- If the data source is Db2 on Linux, UNIX, and Windows systems, the database source generates an error if the external and internal encoding are incompatible, unless the external and internal encoding are Unicode. If the external and internal encoding are Unicode, the database source ignores the internal encoding.
- If the database source is Db2 for z/OS, the database source ignores the internal encoding.

Character data in XML columns is stored in UTF-8 encoding. The database source handles conversion of the data from its internal or external encoding to UTF-8.

Example: The following example demonstrates inserting data from an SQLXML object into an XML column. The data is String data, so the database source treats the data as externally encoded.

```
public void insertSQLXML()
{
    Connection con = DriverManager.getConnection(url);
  SQLXML info = con.createSQLXML();
                            // Create an SQLXML object
  PreparedStatement insertStmt = null;
  String infoData =
    "<customerinfo xmlns=""http://posample.org"" " +
    "Cid=""1000"">…</customerinfo>";
  info.setString(infoData);
                            // Populate the SQLXML object
  int cid = 1000;
  try {
    sqls = "INSERT INTO CUSTOMER (CID, INFO) VALUES (?, ?)";
    insertStmt = con.prepareStatement(sqls);
    insertStmt.setInt(1, cid);
    insertStmt.setSQLXML(2, info);
                            // Assign the SQLXML object value
                                                        // to an input parameter
    if (insertStmt.executeUpdate() != 1) {
      System.out.println("insertSQLXML: No record inserted.");
    }
  }
  catch (IOException ioe) {
   ioe.printStackTrace();
  }
  catch (SQLException sqle) {
    System.out.println("insertSQLXML: SQL Exception: " +
      sqle.getMessage());
    System.out.println("insertSQLXML: SQL State: " +
      sqle.getSQLState());
    System.out.println("insertSQLXML: SQL Error Code: " +
      sqle.getErrorCode());

  }
}
```

Example: The following example demonstrates inserting data from a file into an XML column. The data is inserted as binary data, so the database server honors the internal encoding.

```
public void insertBinStream(Connection conn)
{
  PreparedStatement insertStmt = null;
  String sqls = null;
  int cid = 0;
  Statement stmt=null;
  try {
    sqls = "INSERT INTO CUSTOMER (CID, INFO) VALUES (?, ?)";
    insertStmt = conn.prepareStatement(sqls);
    insertStmt.setInt(1, cid);
    File file = new File(fn);
    insertStmt.setBinaryStream(2,
      new FileInputStream(file), (int)file.length());
```

```
      if (insertStmt.executeUpdate() != 1) {
        System.out.println("insertBinStream: No record inserted.");
      }
    }
    catch (IOException ioe) {
     ioe.printStackTrace();
    }
    catch (SQLException sqle) {
      System.out.println("insertBinStream: SQL Exception: " +
        sqle.getMessage());
      System.out.println("insertBinStream: SQL State: " +
        sqle.getSQLState());
      System.out.println("insertBinStream: SQL Error Code: " +
        sqle.getErrorCode());

    }
  }
```

Example: The following example demonstrates inserting binary XML data from a file into an XML column.

```
…
SQLXML info = conn.createSQLXML();
OutputStream os = info.setBinaryStream ();
FileInputStream fis = new FileInputStream("c7.xml");
int read;
while ((read = fis.read ()) != -1) {
  os.write (read);
}

PreparedStatement insertStmt = null;
String sqls = null;
int cid = 1015;
sqls = "INSERT INTO MyCustomer (Cid, Info) VALUES (?, ?)";
insertStmt = conn.prepareStatement(sqls);
insertStmt.setInt(1, cid);
insertStmt.setSQLXML(2, info);
insertStmt.executeUpdate();
```

Related reference

"Data types that map to database data types in Java applications" on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

XML data retrieval in JDBC applications

In JDBC applications, you use `ResultSet.getXXX` or `ResultSet.getObject` methods to retrieve data from XML columns.

In a JDBC application, you can retrieve data from XML columns in a Db2 table as XML textual data. You can retrieve data from XML columns in a table as binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports binary XML data.

You can use one of the following techniques to retrieve XML data:

- Use the `ResultSet.getSQLXML` method to retrieve the data. Then use a `SQLXML.getXXX` method to retrieve the data into a compatible output data type. This technique requires JDBC 4.0 or later.

  For example, you can retrieve data by using the `SQLXML.getBinaryStream` method or the `SQLXML.getSource` method.
- Use a `ResultSet.getXXX` method other than `ResultSet.getObject` to retrieve the data into a compatible data type.
- Use the `ResultSet.getObject` method to retrieve the data, and then cast it to the `DB2Xml` type and assign it to a `DB2Xml` object. Then use a `DB2Xml.getDB2XXX` or `DB2Xml.getDB2XmlXXX` method to retrieve the data into a compatible output data type.

  You need to use this technique if you are not using a version of the IBM Data Server Driver for JDBC and SQLJ that supports JDBC 4.0.

The following table lists the `ResultSet` methods and corresponding output data types for retrieving XML data.

Table 19. ResultSet methods and data types for retrieving XML data

Method	Output data type
ResultSet.getAsciiStream	InputStream
ResultSet.getBinaryStream	InputStream
ResultSet.getBytes	byte[]
ResultSet.getCharacterStream	Reader
ResultSet.getObject	Object
ResultSet.getSQLXML	SQLXML
ResultSet.getString	String

The following table lists the methods that you can call to retrieve data from a java.sql.SQLXML or a com.ibm.db2.jcc.DB2Xml object, and the corresponding output data types and type of encoding in the XML declarations.

Table 20. SQLXML and DB2Xml methods, data types, and added encoding specifications

Method	Output data type	Type of XML internal encoding declaration added
SQLXML.getBinaryStream	InputStream	None
SQLXML.getCharacterStream	Reader	None
SQLXML.getSource	Source"1" on page 94	None
SQLXML.getString	String	None
DB2Xml.getDB2AsciiStream	InputStream	None
DB2Xml.getDB2BinaryStream	InputStream	None
DB2Xml.getDB2Bytes	byte[]	None
DB2Xml.getDB2CharacterStream	Reader	None
DB2Xml.getDB2String	String	None
DB2Xml.getDB2XmlAsciiStream	InputStream	US-ASCII
DB2Xml.getDB2XmlBinaryStream	InputStream	Specified by `getDB2XmlBinaryStream` *targetEncoding* parameter
DB2Xml.getDB2XmlBytes	byte[]	Specified by DB2Xml.getDB2XmlBytes *targetEncoding* parameter
DB2Xml.getDB2XmlCharacterStream	Reader	ISO-10646-UCS-2
DB2Xml.getDB2XmlString	String	ISO-10646-UCS-2

Note:

1. The class that is returned is specified by the invoker of `getSource`, but the class must extend `javax.xml.transform.Source`.

If the application executes the XMLSERIALIZE function on the data that is to be returned, after execution of the function, the data has the data type that is specified in the XMLSERIALIZE function, not the XML data type. Therefore, the driver handles the data as the specified type and ignores any internal encoding declarations.

Example: The following example demonstrates retrieving data from an XML column into an SQLXML object, and then using the SQLXML.getString method to retrieve the data into a string.

```
public void fetchToSQLXML(long cid, java.sql.Connection conn)
  {
    System.out.println(">> fetchToSQLXML: Get XML data as an SQLXML object " +
    "using getSQLXML");
    PreparedStatement selectStmt = null;
    String sqls = null, stringDoc = null;
    ResultSet rs = null;

    try{
      sqls = "SELECT info FROM customer WHERE cid = " + cid;
      selectStmt = conn.prepareStatement(sqls);
      rs = selectStmt.executeQuery();

      // Get metadata
      // Column type for XML column is the integer java.sql.Types.OTHER
      ResultSetMetaData meta = rs.getMetaData();
      int colType = meta.getColumnType(1);
      System.out.println("fetchToSQLXML: Column type = " + colType);
      while (rs.next()) {
        // Retrieve the XML data with getSQLXML.
        // Then write it to a string with
        // explicit internal ISO-10646-UCS-2 encoding.
        java.sql.SQLXML xml = rs.getSQLXML(1);
        System.out.println (xml.getString());
      }
      rs.close();
    }
    catch (SQLException sqle) {
      System.out.println("fetchToSQLXML: SQL Exception: " +
        sqle.getMessage());
      System.out.println("fetchToSQLXML: SQL State: " +
        sqle.getSQLState());
      System.out.println("fetchToSQLXML: SQL Error Code: " +
        sqle.getErrorCode());
    }
  }
```

Example: The following example demonstrates retrieving data from an XML column into an SQLXML object, and then using the SQLXML.getBinaryStream method to retrieve the data as binary data into an InputStream.

```
String sql = "SELECT INFO FROM Customer WHERE Cid='1000'";
PreparedStatement pstmt = con.prepareStatement(sql);
ResultSet resultSet = pstmt.executeQuery();
// Get the result XML as a binary stream
SQLXML sqlxml = resultSet.getSQLXML(1);
InputStream binaryStream = sqlxml.getBinaryStream();
```

Example: The following example demonstrates retrieving data from an XML column into a String variable.

```
public void fetchToString(long cid, java.sql.Connection conn)
  {
    System.out.println(">> fetchToString: Get XML data " +
    "using getString");
    PreparedStatement selectStmt = null;
    String sqls = null, stringDoc = null;
    ResultSet rs = null;

    try{
      sqls = "SELECT info FROM customer WHERE cid = " + cid;
      selectStmt = conn.prepareStatement(sqls);
      rs = selectStmt.executeQuery();

      // Get metadata
      // Column type for XML column is the integer java.sql.Types.OTHER
      ResultSetMetaData meta = rs.getMetaData();
      int colType = meta.getColumnType(1);
      System.out.println("fetchToString: Column type = " + colType);

      while (rs.next()) {
        stringDoc = rs.getString(1);
        System.out.println("Document contents:");
        System.out.println(stringDoc);
  }
```

```
    catch (SQLException sqle) {
      System.out.println("fetchToString: SQL Exception: " +
        sqle.getMessage());
      System.out.println("fetchToString: SQL State: " +
        sqle.getSQLState());
      System.out.println("fetchToString: SQL Error Code: " +
        sqle.getErrorCode());
    }
  }
```

Example: The following example demonstrates retrieving data from an XML column into a `DB2Xml` object, and then using the `DB2Xml.getDB2XmlString` method to retrieve the data into a string with an added XML declaration with an ISO-10646-UCS-2 encoding specification.

```
public void fetchToDB2Xml(long cid, java.sql.Connection conn)
  {
    System.out.println(">> fetchToDB2Xml: Get XML data as a DB2XML object " +
    "using getObject");
    PreparedStatement selectStmt = null;
    String sqls = null, stringDoc = null;
    ResultSet rs = null;

    try{
      sqls = "SELECT info FROM customer WHERE cid = " + cid;
      selectStmt = conn.prepareStatement(sqls);
      rs = selectStmt.executeQuery();

      // Get metadata
      // Column type for XML column is the integer java.sql.Types.OTHER
      ResultSetMetaData meta = rs.getMetaData();
      int colType = meta.getColumnType(1);
      System.out.println("fetchToDB2Xml: Column type = " + colType);
      while (rs.next()) {
        // Retrieve the XML data with getObject, and cast the object
        // as a DB2Xml object. Then write it to a string with
        // explicit internal ISO-10646-UCS-2 encoding.
        com.ibm.db2.jcc.DB2Xml xml =
          (com.ibm.db2.jcc.DB2Xml) rs.getObject(1);
        System.out.println (xml.getDB2XmlString());
      }
      rs.close();
    }
    catch (SQLException sqle) {
      System.out.println("fetchToDB2Xml: SQL Exception: " +
        sqle.getMessage());
      System.out.println("fetchToDB2Xml: SQL State: " +
        sqle.getSQLState());
      System.out.println("fetchToDB2Xml: SQL Error Code: " +
        sqle.getErrorCode());
    }
  }
```

Related reference

“Data types that map to database data types in Java applications” on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

Invocation of routines with XML parameters in Java applications

Java applications can call stored procedures at Db2 on Linux, UNIX, and Windows systems or Db2 for z/OS data sources that have XML parameters.

For native SQL procedures, XML parameters in the stored procedure definition have the XML type. For external stored procedures and user-defined functions on Db2 on Linux, UNIX, and Windows systems data sources, XML parameters in the routine definition have the XML AS CLOB type. When you call a stored procedure or user-defined function that has XML parameters, you need to use a compatible data type in the invoking statement.

To call a routine with XML input parameters from a JDBC program, use parameters of the java.sql.SQLXML or com.ibm.db2.jcc.DB2Xml type. To register XML output parameters, register the parameters as the java.sql.Types.SQLXML or com.ibm.db2.jcc.DB2Types.XML type. (The com.ibm.db2.jcc.DB2Xml and com.ibm.db2.jcc.DB2Types.XML types are deprecated.)

Example: JDBC program that calls a stored procedure that takes three XML parameters: an IN parameter, an OUT parameter, and an INOUT parameter. This example requires JDBC 4.0 or later.

```
java.sql.SQLXML in_xml = xmlvar;
java.sql.SQLXML out_xml = null;
java.sql.SQLXML inout_xml = xmlvar;
                                  // Declare an input, output, and
                                  // INOUT XML parameter
Connection con;
CallableStatement cstmt;
ResultSet rs;
…
cstmt = con.prepareCall("CALL SP_xml(?,?,?)");
                                  // Create a CallableStatement object
cstmt.setObject (1, in_xml);      // Set input parameter
cstmt.setObject (3, inout_xml);   // Set inout parameter
cstmt.registerOutParameter (2, java.sql.Types.SQLXML);
                                  // Register out and input parameters
cstmt.registerOutParameter (3, java.sql.Types.SQLXML);
cstmt.executeUpdate();            // Call the stored procedure
out_xml = cstmt.getSQLXML(2);     // Get the OUT parameter value
inout_xml = cstmt.getSQLXML(3);   // Get the INOUT parameter value
System.out.println("Parameter values from SP_xml call: ");
System.out.println("Output parameter value ");
MyUtilities.printString(out_xml.getString());
                           // Use the SQLXML.getString
                           // method to convert the out_xml
                           // value to a string for printing.
                           // Call a user-defined method called
                           // printString (not shown) to print
                           // the value.
System.out.println("INOUT parameter value ");
MyUtilities.printString(inout_xml.getString());
                           // Use the SQLXML.getString
                           // method to convert the inout_xml
                           // value to a string for printing.
                           // Call a user-defined method called
                           // printString (not shown) to print
                           // the value.
```

To call a routine with XML parameters from an SQLJ program, use parameters of the java.sql.SQLXML or com.ibm.db2.jcc.DB2Xml type.

Example: SQLJ program that calls a stored procedure that takes three XML parameters: an IN parameter, an OUT parameter, and an INOUT parameter. This example requires JDBC 4.0 or later.

```
java.sql.SQLXML in_xml = xmlvar;
java.sql.SQLXML out_xml = null;
java.sql.SQLXML inout_xml = xmlvar;
                                  // Declare an input, output, and
                                  // INOUT XML parameter
…
#sql [myConnCtx] {CALL SP_xml(:IN in_xml,
                              :OUT out_xml,
                              :INOUT inout_xml)};
                                  // Call the stored procedure
System.out.println("Parameter values from SP_xml call: ");
System.out.println("Output parameter value ");
MyUtilities.printString(out_xml.getString());
                           // Use the SQLXML.getString
                           // method toconvert the out_xml value
                           // to a string for printing.
                           // Call a user-defined method called
                           // printString (not shown) to print
                           // the value.
System.out.println("INOUT parameter value ");
MyUtilities.printString(inout_xml.getString());
                           // Use the SQLXML.getString
                           // method to convert the inout_xml
                           // value to a string for printing.
                           // Call a user-defined method called
                           // printString (not shown) to print
                           // the value.
```

Binary XML format in Java applications

The IBM Data Server Driver for JDBC and SQLJ can send XML data to the data server or retrieve XML data from the data server as binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format). The data server must provide support for binary XML data.

The IBM Data Server Driver for JDBC and SQLJ presents binary XML data to the application only through XML object interfaces. The user does not see the data in the binary XML format.

The format of XML data is transparent to the application. Storage and retrieval of binary XML data requires version 4.9 or later of the IBM Data Server Driver for JDBC and SQLJ. If you are using binary XML data in SQLJ applications, you also need version 4.9 or later of the sqlj4.zip package.

You use the property xmlFormat to control whether the data format for retrieval of XML data is textual XML format or binary XML format. You set xmlFormat to XML_FORMAT_BINARY (1) to enable binary XML format. The default is textual XML format.

For update of data in XML table columns, xmlFormat has no effect. If the input data is binary XML data, and the data server does not support binary XML data, the input data is converted to textual XML data. Otherwise, no conversion occurs.

When binary XML data is used, the XML data that is passed to the IBM Data Server Driver for JDBC and SQLJ cannot refer to external entities, internal entities, or internal DTDs. External DTDs are supported only if those DTDs were previously registered in the data source.

There is no `setXXX` method defined on the `Connection` interface for the xmlFormat property. Therefore, to set the xmlFormat value when you use the `Connection` interface, you need to specify xmlFormat as a property when you execute the `DriverManager.getConnection` method. For example:

```
properties.put("xmlFormat", "1");
DriverManager.getConnection(url, properties);
```

Restriction: When you send XML data in binary format to a Db2 for z/OS data server that supports binary XML data, you cannot use an `InputStreamReader` object with a `Charset` object named UTF-16LE, UTF-8, or UTF-16BE for an XML document file that contains a byte order mark (BOM). To circumvent this restriction, take one of the following actions:

- Remove the BOM from the XML instance document in the input file.
- Use an `InputStreamReader` object with a `Charset` object named UTF-16 for the input file.
- Use an `InputStream` object instead of an `InputStreamReader` object for the input file.

Binary XML format is most efficient for cases in which the input or output data is in a non-textual representation, such as SAX, StAX, or DOM. For example, these methods retrieve XML data in non-textual representations:

- getSource(SAXSource.class)
- getSource(StAXSource.class)
- getSource(DOMSource.class)

These methods update XML columns with data in non-textual representations:

- setResult(SAXResult.class)
- setResult(StAXResult.class)
- setResult(DOMResult.class)

The SAX representation is the most efficient way to retrieve data that is in the binary XML format because the data does not undergo extra conversions from binary format to textual format.

Suppose that you set xmlFormat to XML_FORMAT_BINARY (1). In the following JDBC example, the IBM Data Server Driver for JDBC and SQLJ retrieves data in the binary XML format, application uses the SAX parser to parse the retrieved data.

```
…
Statement stmt = conn.createStatement();
ResultSet rs = stmt.executeQuery("SELECT XMLCOL FROM XMLTABLE");
ContentHandler handler = new MyContentHandler();
while (rs.next()) {
    SQLXML sqlxml = rs.getSQLXML(1);
    SAXSource source = sqlxml.getSource(SAXSource.class);
    XMLReader reader = source.getXMLReader();
    reader.setContentHandler(handler);
    reader.parse(source.getInputSource());
}
…
```

The following SQLJ example performs the same actions.

```
#sql iterator  SqlXmlIter(java.sql.SQLXML);
{
 …
 SqlXmlIter SQLXMLiter = null;
 java.sql.SQLXML outSqlXml = null;
 ContentHandler handler = new MyContentHandler();
 #sql [ctx] SQLXmlIter = {SELECT XMLCOL FROM XMLTABLE};
 #sql {FETCH :SqlXmlIter INTO :outSqlXml};
 while (!SQLXMLIter.endFetch()) {
  SAXSource source = outSqlXml.getSource(SAXSource.class);
  XMLReader reader = source.getXMLReader();
  reader.setContentHandler(handler);
  reader.parse(source.getInputSource());
  #sql {FETCH :SqlXmlIter INTO :outSqlXml};
 }
 …
}
```

Java support for XML schema registration and removal

The IBM Data Server Driver for JDBC and SQLJ provides methods that let you write Java application programs to register and remove XML schemas and their components.

The methods are:

>DB2Connection.registerDB2XMLSchema
Registers an XML schema in the database manager, using one or more XML schema documents. There are two forms of this method: one form for XML schema documents that are input from `InputStream` objects, and one form for XML schema documents that are in a `String`.

>DB2Connection.deregisterDB2XMLObject
Removes an XML schema definition from the database manager.

>DB2Connection.updateDB2XmlSchema
Replaces the XML schema documents in a registered XML schema with the XML schema documents from another registered XML schema. Optionally drops the XML schema whose contents are copied. This method is available only for connections to Db2 on Linux, UNIX, and Windows systems.

Before you can invoke these methods, the stored procedures that support these methods must be installed on the data server.

Example: Registration of an XML schema: The following example demonstrates the use of registerDB2XmlSchema to register an XML schema in Db2, using a single XML schema document (customer.xsd) that is read from an input stream. The SQL schema name for the registered schema is SYSXSR. The *xmlSchemaLocations* value is null, so Db2 will not find this XML schema on an invocation of DSN_XMLVALIDATE that supplies a non-null XML schema location value. No additional properties are registered.

```
public static void registerSchema(
  Connection con,
  String schemaName)
```

```
  throws SQLException {
  // Define the registerDB2XmlSchema parameters
  String[] xmlSchemaNameQualifiers = new String[1];
  String[] xmlSchemaNames = new String[1];
  String[] xmlSchemaLocations = new String[1];
  InputStream[] xmlSchemaDocuments = new InputStream[1];
  int[] xmlSchemaDocumentsLengths = new int[1];
  java.io.InputStream[] xmlSchemaDocumentsProperties = new InputStream[1];
  int[] xmlSchemaDocumentsPropertiesLengths = new int[1];
  InputStream xmlSchemaProperties;
  int xmlSchemaPropertiesLength;
  //Set the parameter values
  xmlSchemaLocations[0] = "";
  FileInputStream fi = null;
  xmlSchemaNameQualifiers[0] = "SYSXSR";
  xmlSchemaNames[0] = schemaName;
  try {
    fi = new FileInputStream("customer.xsd");
    xmlSchemaDocuments[0] = new BufferedInputStream(fi);
  } catch (FileNotFoundException e) {
        e.printStackTrace();
  }
  try {
     xmlSchemaDocumentsLengths[0] = (int) fi.getChannel().size();
     System.out.println(xmlSchemaDocumentsLengths[0]);
  } catch (IOException e1) {
        e1.printStackTrace();
  }
  xmlSchemaDocumentsProperties[0] = null;
  xmlSchemaDocumentsPropertiesLengths[0] = 0;
  xmlSchemaProperties = null;
  xmlSchemaPropertiesLength = 0;
  DB2Connection ds = (DB2Connection) con;
  // Invoke registerDB2XmlSchema
  ds.registerDB2XmlSchema(
    xmlSchemaNameQualifiers,
    xmlSchemaNames,
    xmlSchemaLocations,
    xmlSchemaDocuments,
    xmlSchemaDocumentsLengths,
    xmlSchemaDocumentsProperties,
    xmlSchemaDocumentsPropertiesLengths,
    xmlSchemaProperties,
    xmlSchemaPropertiesLength,
    false);
}
```

Example: Removal of an XML schema: The following example demonstrates the use of deregisterDB2XmlObject to remove an XML schema from Db2. The SQL schema name for the registered schema is SYSXSR.

```
public static void deregisterSchema(
  Connection con,
  String schemaName)
  throws SQLException {
  // Define and assign values to the deregisterDB2XmlObject parameters
  String xmlSchemaNameQualifier = "SYSXSR";
  String xmlSchemaName = schemaName;
  DB2Connection ds = (DB2Connection) con;
  // Invoke deregisterDB2XmlObject
  ds.deregisterDB2XmlObject(
    xmlSchemaNameQualifier,
    xmlSchemaName);
}
```

Example: Update of an XML schema: The following example applies only to connections to Db2 on Linux, UNIX, and Windows systems. It demonstrates the use of updateDB2XmlSchema to update the contents of an XML schema with the contents of another XML schema. The schema that is copied is kept in the repository. The SQL schema name for both registered schemas is SYSXSR.

```
public static void updateSchema(
  Connection con,
  String schemaNameTarget,
  String schemaNameSource)
  throws SQLException {
  // Define and assign values to the updateDB2XmlSchema parameters
  String xmlSchemaNameQualifierTarget = "SYSXSR";
```

```
  String xmlSchemaNameQualifierSource = "SYSXSR";
  String xmlSchemaNameTarget = schemaNameTarget;
  String xmlSchemaNameSource = schemaNameSource;
  boolean dropSourceSchema = false;
  DB2Connection ds = (DB2Connection) con;
  // Invoke updateDB2XmlSchema
  ds.updateDB2XmlSchema(
    xmlSchemaNameQualifierTarget,
    xmlSchemaNameTarget,
        xmlSchemaNameQualifierSource,
        xmlSchemaNameSource,
    dropSourceSchema);
}
```

Bidirectional (BiDi) text layout transformation

The IBM BiDi (bidirectional) engine can perform BiDi Layout transformation on data being stored and retrieved from the database.

The IBM Bidi engine bases text transformations on the following characteristics of text data:

- Numeral shape (Arabic or Hindi)
- Orientation (right-to-left or left-to-right)
- Shaping (shaped or unshaped)
- Symmetric swapping (yes or no)
- Text type (logical or visual)

Enable Bidi text layout transformation for your database by setting the enableBidiLayoutTransformation, clientBidiStringType, and serverBidiStringType properties on a Connection or DataSource. Set enableBidiLayoutTransformation to `true`, then specify the String type of the client application and data server with the clientBidiStringType and serverBidiStringType properties respectively. The following table summarizes which string type values to specify for particular combinations of text data attributes.

Table 21. String type values and corresponding attributes for the clientBidiStringType and serverBidiStringType properties

		Text Attributes				
String type value integer constant	**String type value**	**Type of text**	**Orientation**	**Symmetric swapping**	**Numeral shape**	**Text shapes**
4	`DB2BaseDataSource.BIDI_ST4`	Visual	Left-to-right	No	Nominal	Shaped
5	`DB2BaseDataSource.BIDI_ST5`	Implicit	Left-to-right	Yes	Nominal	Nominal
6	`DB2BaseDataSource.BIDI_ST6`	Implicit	Right-to-left	Yes	Nominal	Nominal

Table 21. String type values and corresponding attributes for the clientBidiStringType and serverBidiStringType properties (continued)

		Text Attributes				
String type value integer constant	**String type value**	**Type of text**	**Orientation**	**Symmetric swapping**	**Numeral shape**	**Text shapes**
7	`DB2BaseDataSource.BIDI_ST7`	Visual	Right-to-left	No	Nominal	Shaped
8	`DB2BaseDataSource.BIDI_ST8`	Visual	Right-to-left	No	Nominal	Shaped
9	`DB2BaseDataSource.BIDI_ST9`	Implicit	Right-to-left	Yes	Nominal	Shaped
10	`DB2BaseDataSource.BIDI_ST10`	Implicit	Contextual left-to-right	Yes	Nominal	Nominal
11	`DB2BaseDataSource.BIDI_ST11`	Implicit	Contextual right-to-left	Yes	Nominal	Nominal

BiDi text layout transformations can be performed on:

- Strings enclosed in single apostrophes in SQL statements:

```
ResultSet rs = st.executeQuery( "SELECT * FROM PARAM.JCCTEST WHERE

product=' <text_to_transform> '")
```

- Parameter values for PreparedStatements and CallableStatements:

```
        Connection conn = null;

        PreparedStatement pstmt =

conn.prepareStatement( "SELECT PRODCUT FROM PARAM.JCCTEST WHERE PRODCUT=?" );
        pstmt.setString(1,  "<text_to_transform>" );
```

- Values retrieved through `getXXX()` methods on ResultSet and CallableStatement objects:

```
        ResultSet rs = pstmt.executeQuery();

        while (rs.next()){
          System.out.println(rs.getString(1));
```

```
        // BiDi layout transformation will be performed the on

return value from getString()
       }
```

Inserting data from file reference variables into tables in JDBC applications

You can use file reference variable objects with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9 or later to stream LOB or XML input data.

Before you begin

You need to store your LOB or XML input data in HFS files.

About this task

Use of file reference variables eliminates the need to materialize the LOB or XML data in memory before the data is stored in tables.

Procedure

To use file reference variables to store LOB or XML data in tables, follow these steps:

1. Invoke the `Connection.prepareStatement` method to create a `PreparedStatement` object from an INSERT statement.

   The parameter markers in the INSERT statement represent XML or LOB values.
2. Execute constructors for file reference variable objects of the appropriate types.

   The following table lists the types of data in the input files and the appropriate constructors.

Input data type	Constructor
BLOB	com.ibm.db2.jcc.DB2BlobFileReference
CLOB	com.ibm.db2.jcc.DB2ClobFileReference
XML AS BLOB	com.ibm.db2.jcc.DB2XmlAsBlobFileReference
XML AS CLOB	com.ibm.db2.jcc.DB2XmlAsClobFileReference

   The first parameter in each constructor must specify the absolute path name for an existing HFS file.
3. If you are performing single-row INSERT operations, repeat these steps for each row that you want to insert:
   a) Invoke `DB2PreparedStatement.setXXX` to pass values to the input variables. Alternatively, you can use `PreparedStatement.setObject` methods.

      The following table lists the types of data in the input files and the appropriate `DB2PreparedStatement.setXXX` methods to use for each data type.

Input data type	DB2PreparedStatement.setXXX method
BLOB	setDB2BlobFileReference
CLOB	setDB2ClobFileReference
XML AS BLOB	setDB2XmlAsBlobFileReference
XML AS CLOB	setDB2XmlAsClobFileReference

If you use DB2PreparedStatement methods, you need to cast the PreparedStatement object that you created in step "1" on page 103 to a DB2PreparedStatement object when you execute a DB2PreparedStatement.setXXX method.

You can assign NULL values to input parameters in any of the following ways:

- Using DB2PreparedStatement.setXXX methods, with null as the *fileRef* parameter value.
- Using PreparedStatement.setObject, with null as the *x* (second) parameter value and the appropriate value from com.ibm.db2.jcc.DB2Types for the *targetJdbcType* (third) parameter value.
- Using PreparedStatement.setNull, with the appropriate value from com.ibm.db2.jcc.DB2Types for the *JdbcType* (second) parameter value.

b) Invoke the PreparedStatement.execute or PreparedStatement.executeUpdate method to update the table with the variable values.

4. If you are performing multi-row INSERT operations, execute these steps:
   a) Repeat these steps for every row that you want to insert:
      i) Invoke DB2PreparedStatement.setXXX to pass values to the input variables. Alternatively, you can use PreparedStatement.setObject methods.
      ii) Invoke the PreparedStatement.addBatch method after you set the values for a row of the table.
   b) Invoke the PreparedStatement.executeBatch method to update the table with the variable values.
5. Invoke the PreparedStatement.close method to close the PreparedStatement object when you have finished using that object.

Examples

The following code inserts a single row into a table. The code inserts values from CLOB and BLOB file reference variables into CLOB and BLOB columns and a NULL value into an XML column. The numbers to the right of selected statements correspond to the previously-described steps.

```
Connection conn;
…
PreparedStatement pstmt =
  conn.prepareStatement(
    "INSERT INTO TEST02TB(RECID,CLOBCOL,BLOBCOL,XMLCOL) VALUES('003',?,?,?)");
                          // Create a PreparedStatement object             1
com.ibm.db2.jcc.DB2ClobFileReference clobFileRef =
  new com.ibm.db2.jcc.DB2ClobFileReference("/u/usrt001/jcc/test/TEXT.FILE","Cp037");
com.ibm.db2.jcc.DB2BlobFileReference blobFileRef =
  new com.ibm.db2.jcc.DB2BlobFileReference("/u/usrt001/jcc/test/BINARY.FILE");
com.ibm.db2.jcc.DB2XmlAsBlobFileReference xmlAsBlobFileRef =
  new com.ibm.db2.jcc.DB2XmlAsBlobFileReference(
  "/u/usrt001/jcc/test/XML.FILE");
                          // Execute constructors for the file reference   2
                          // variable objects
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setDB2ClobFileReference(1,clobFileRef);
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setDB2BlobFileReference(2,blobFileRef);
pstmt.setNull(3,com.ibm.db2.jcc.DB2Types.XML_AS_BLOB_FILE);
                          // Assign values to the CLOB and BLOB parameters. 3a
                          // Assign a null value to the XML parameter.
int numUpd = pstmt.executeUpdate();
                          // Perform the update                            3b
pstmt.close();            // Close the PreparedStatement object            5
```

The following code uses multi-row INSERT to insert two rows in a table. The code inserts values from XML AS CLOB and XML AS BLOB file reference variables into XML columns. The numbers to the right of selected statements correspond to the previously-described steps.

```
Connection conn;
…
PreparedStatement pstmt =
  conn.prepareStatement(
    "INSERT INTO TEST03TB(RECID,XMLCLOBCOL,XMLBLOBCOL) VALUES('003',?,?)");
```

```
                          // Create a PreparedStatement object              1
com.ibm.db2.jcc.DB2XmlAsClobFileReference xmlAsClobFileRef1 =
  new com.ibm.db2.jcc.DB2XmlAsClobFileReference("/u/usrt001/jcc/test/XMLCLOB1.FILE","Cp037");
com.ibm.db2.jcc.DB2XmlAsBlobFileReference xmlAsBlobFileRef1 =
  new com.ibm.db2.jcc.DB2XmlAsBlobFileReference("/u/usrt001/jcc/test/XMLBLOB1.FILE");
com.ibm.db2.jcc.DB2XmlAsClobFileReference xmlAsClobFileRef2 =
  new com.ibm.db2.jcc.DB2XmlAsClobFileReference("/u/usrt001/jcc/test/XMLCLOB2.FILE","Cp037");
com.ibm.db2.jcc.DB2XmlAsBlobFileReference xmlAsBlobFileRef2 =
  new com.ibm.db2.jcc.DB2XmlAsBlobFileReference("/u/usrt001/jcc/test/XMLBLOB2.FILE");
                          // Execute constructors for the file reference    2
                          // variable objects
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setDB2ClobFileReference(1,xmlAsClobFileRef1);
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setDB2BlobFileReference(2,xmlAsBlobFileRef1);
                          // Assign first set of values to the              4ai
                          // XML parameters
pstmt.addBatch();         // Add the first input parameters to the batch    4aii
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setDB2ClobFileReference(1,xmlAsClobFileRef2);
((com.ibm.db2.jcc.DB2PreparedStatement)pstmt).setDB2BlobFileReference(2,xmlAsBlobFileRef2);
                          // Assign second set of values to the             4ai
                          // XML parameters
pstmt.addBatch();         // Add the second input parameters to the batch   4aii
int [] numUpd = pstmt.executeBatch();
                          // Perform the update                             4b
pstmt.close();            // Close the PreparedStatement object             5
```

Loading a Db2 for z/OS table by using an IBM Data Server Driver for JDBC and SQLJ method

The DB2Connection.zLoad method lets you load a Db2 for z/OS table from a Java application.

Procedure

To load a Db2 for z/OS from a Java application, follow these steps:

1. Cast the Connection object for the connection to the data server to a DB2Connection object.
2. Specify the LOAD statement, the name of the file that contains the input data in variables, and optionally, the utility ID for the load job.

   You can specify the LOAD statement in a variable, or in a file.

   - To specify the LOAD statement in a variable, use a form of the zLoad method without the *isLoadstmtInFile* variable, or specify a form of the zLoad method with *isLoadstmtInFile* set to false.
   - To specify the LOAD statement in a file, use a form of the zLoad method with *isLoadstmtInFile* set to true. Provide the complete path of the file that contains the LOAD statement in the *loadstmtOrFile* variable.
3. Issue the DB2Connection.zLoad method.
4. Retrieve the return code and error messages from the LoadResult object that the DB2Connection.zLoad method returned.

Examples

Example: Use a LOAD statement from a variable to load data from file customer.data into table MYID.CUSTOMER_DATA.

The numbers to the right of statements correspond to the previously described steps.

```
import java.sql.*;                        // JDBC base
import com.ibm.db2.jcc.*;                 // IBM Data Server Driver for JDBC
                                          // and SQLJ implementation of JDBC
...
DB2Connection db2conn = (DB2Connection)con;                              1
String loadstmt = "TEMPLATE SORTIN DSN &JO..&ST..SORTIN.T&TIME. " +      2
 "UNIT SYSVIO SPACE(10,10) CYL DISP(NEW,DELETE,DELETE) " +
 "TEMPLATE SORTOUT DSN &JO..&ST..SORTOUT.T&TIME. UNIT SYSVIO " +
 "SPACE(10,10) CYL DISP(NEW,DELETE,DELETE) LOAD DATA INDDN "   +
 "SYSCLIEN WORKDDN(SORTIN) REPLACE PREFORMAT LOG(NO) REUSE " +
 "NOCOPYPEND FORMAT DELIMITED UNICODE " +
 "INTO TABLE MYID.CUSTOMER_DATA NUMRECS 30000";
```

```
                                        // LOAD statement text is
                                        // in a string
String dataFilename = "C:\\customer.data";
                                        // Name of the file that contains
                                        // the input data
String utilid = "ZLOADTEST1";
                                        // Identifier for this run of the
                                        // LOAD utility
LoadResult lr = db2conn.zLoad(loadstmt, dataFilename, utilid);          3
int returnCode = lr.getReturnCode();                                    4
String loadMessage = lr.getMessage();
```

Example: Use a LOAD statement from a file to load data from file customer.data into table MYID.CUSTOMER_DATA.

The numbers to the right of statements correspond to the previously described steps.

```
import java.sql.*;                      // JDBC base
import com.ibm.db2.jcc.*;               // IBM Data Server Driver for JDBC
                                        // and SQLJ implementation of JDBC
...
DB2Connection db2conn = (DB2Connection)con;                             1
String loadstmtOrFile="C:\\Program Files\\IBM\\SQLLIB\\loadStatement.txt"; 2
                                        // Name of the file that contains
                                        // the LOAD statement
Boolean isLoadstmtInFile=true;
                                        // Indicate that the LOAD statement
                                        // is in a file
String dataFilename="C:\\Customer.delimiter.large”;
                                        // Name of the file that contains
                                        // the input data
String utilid="ZLOADTEST2”;
                                        // Identifier for this run of the
                                        // LOAD utility
LoadResult lr =
  db2conn.zLoad(loadstmtOrFile, isLoadstmtInFile, filename, utilid);    3
int returnCode = lr.getReturnCode();                                    4
String loadMessage = lr.getMessage();
```

Transaction control in JDBC applications

In JDBC applications, as in other types of SQL applications, transaction control involves explicitly or implicitly committing and rolling back transactions, and setting the isolation level for transactions.

IBM Data Server Driver for JDBC and SQLJ isolation levels

The IBM Data Server Driver for JDBC and SQLJ supports a number of isolation levels, which correspond to database server isolation levels.

JDBC isolation levels can be set for a unit of work within a JDBC program, using the `Connection.setTransactionIsolation` method. The default isolation level can be set with the defaultIsolationLevel property.

The following table shows the values of *level* that you can specify in the `Connection.setTransactionIsolation` method and their Db2 database server equivalents.

Table 22. Equivalent JDBC and Db2 isolation levels

JDBC value	Db2 isolation level
java.sql.Connection.TRANSACTION_SERIALIZABLE	Repeatable read
java.sql.Connection.TRANSACTION_REPEATABLE_READ	Read stability
java.sql.Connection.TRANSACTION_READ_COMMITTED	Cursor stability
java.sql.Connection.TRANSACTION_READ_UNCOMMITTED	Uncommitted read

The following table shows the values of *level* that you can specify in the `Connection.setTransactionIsolation` method and their IBM Informix equivalents.

Table 23. Equivalent JDBC and IBM Informix isolation levels

JDBC value	IBM Informix isolation level
java.sql.Connection.TRANSACTION_SERIALIZABLE	Repeatable read
java.sql.Connection.TRANSACTION_REPEATABLE_READ	Repeatable read
java.sql.Connection.TRANSACTION_READ_COMMITTED	Committed read
java.sql.Connection.TRANSACTION_READ_UNCOMMITTED	Dirty read
com.ibm.db2.jcc.DB2Connection.TRANSACTION_IDS_CURSOR_STABILITY	IBM Informix cursor stability
com.ibm.db2.jcc.DB2Connection.TRANSACTION_IDS_LAST_COMMITTED	Committed read, last committed

Related concepts

"JDBC connection objects" on page 23
When you connect to a data source by either connection method, you create a `Connection` object, which represents the connection to the data source.

Committing or rolling back JDBC transactions

In JDBC, to commit or roll back transactions explicitly, use the `commit` or `rollback` methods.

About this task

For example:

```
  Connection con;
  …
con.commit();
```

If autocommit mode is on, the database manager performs a commit operation after every SQL statement completes. To set autocommit mode on, invoke the `Connection.setAutoCommit(true)` method. To set autocommit mode off, invoke the `Connection.setAutoCommit(false)` method. To determine whether autocommit mode is on, invoke the `Connection.getAutoCommit` method.

Connections that participate in distributed transactions cannot invoke the `setAutoCommit(true)` method.

When you change the autocommit state, the database manager executes a commit operation, if the application is not already on a transaction boundary.

While a connection is participating in a distributed or global transaction, the associated application cannot issue the `commit` or `rollback` methods.

While a connection is participating in a global transaction, the associated application cannot invoke the `setAutoCommit(true)` method.

Related concepts

"Savepoints in JDBC applications" on page 71
An SQL savepoint represents the state of data and schemas at a particular point in time within a unit of work. You can use SQL statements to set a savepoint, release a savepoint, and restore data and schemas to the state that the savepoint represents.

Related tasks

"Disconnecting from data sources in JDBC applications" on page 117
When you have finished with a connection to a data source, it is *essential* that you close the connection to the data source. Doing this releases the `Connection` object's database and JDBC resources immediately.

"Making batch updates in JDBC applications" on page 33

With batch updates, instead of updating rows of a table one at a time, you can direct JDBC to execute a group of updates at the same time. Statements that can be included in the same batch of updates are known as *batchable* statements.

Default JDBC autocommit modes

The default autocommit mode depends on the data source to which the JDBC application connects.

Autocommit default for Db2 data sources

For connections to Db2 data sources, the default autocommit mode is `true`.

Autocommit default for IBM Informix data sources

For connections to IBM Informix data sources, the default autocommit mode depends on the type of data source. The following table shows the defaults.

Table 24. Default autocommit modes for IBM Informix data sources

Type of data source	Default autocommit mode for local transactions	Default autocommit mode for global transactions
ANSI-compliant database	true	false
Non-ANSI-compliant database without logging	false	not applicable
Non-ANSI-compliant database with logging	true	false

Exceptions and warnings under the IBM Data Server Driver for JDBC and SQLJ

In JDBC applications, SQL errors throw exceptions, which you handle using `try/catch` blocks. SQL warnings do not throw exceptions, so you need to invoke methods to check whether warnings occurred after you execute SQL statements.

The IBM Data Server Driver for JDBC and SQLJ provides the following classes and interfaces, which provide information about errors and warnings.

SQLException

The `SQLException` class for handling errors. All JDBC methods throw an instance of `SQLException` when an error occurs during their execution. According to the JDBC specification, an `SQLException` object contains the following information:

- An `int` value that contains an error code. `SQLException.getErrorCode` retrieves this value.
- A `String` object that contains the SQLSTATE, or null. `SQLException.getSQLState` retrieves this value.
- A `String` object that contains a description of the error, or null. `SQLException.getMessage` retrieves this value.
- A pointer to the next `SQLException`, or null. `SQLException.getNextException` retrieves this value.

When a JDBC method throws a single `SQLException`, that `SQLException` might be caused by an underlying Java exception that occurred when the IBM Data Server Driver for JDBC and SQLJ processed the method. In this case, the `SQLException` wraps the underlying exception, and you can use the `SQLException.getCause` method to retrieve information about the error.

DB2Diagnosable

The IBM Data Server Driver for JDBC and SQLJ-only interface `com.ibm.db2.jcc.DB2Diagnosable` extends the `SQLException` class. The `DB2Diagnosable` interface gives you more information about errors that occur when the data source is accessed. If the JDBC driver detects an error, `DB2Diagnosable` gives you the same information as the standard `SQLException` class. However, if the database server detects the error, `DB2Diagnosable` adds the following methods, which give you additional information about the error:

getSqlca
Returns an `DB2Sqlca` object with the following information:

- An SQL error code
- The SQLERRMC values
- The SQLERRP value
- The SQLERRD values
- The SQLWARN values
- The SQLSTATE

getThrowable
Returns a `java.lang.Throwable` object that caused the `SQLException`, or null, if no such object exists.

printTrace
Prints diagnostic information.

SQLException subclasses

If you are using JDBC 4.0 or later, you can obtain more specific information than an `SQLException` provides by catching the following exception classes:

- `SQLNonTransientException`

  An `SQLNonTransientException` is thrown when an SQL operation that failed previously cannot succeed when the operation is retried, unless some corrective action is taken. The `SQLNonTransientException` class has these subclasses:

  - `SQLFeatureNotSupportedException`
  - `SQLNonTransientConnectionException`
  - `SQLDataException`
  - `SQLIntegrityConstraintViolationException`
  - `SQLInvalidAuthorizationSpecException`
  - `SQLSyntaxException`
- `SQLTransientException`

  An `SQLTransientException` is thrown when an SQL operation that failed previously might succeed when the operation is retried, without intervention from the application. A connection is still valid after an `SQLTransientException` is thrown. The `SQLTransientException` class has these subclasses:

  - `SQLTransientConnectionException`
  - `SQLTransientRollbackException`
  - `SQLTimeoutException`
- `SQLRecoverableException`

  An `SQLRecoverableException` is thrown when an operation that failed previously might succeed if the application performs some recovery steps, and retries the transaction. A connection is no longer valid after an `SQLRecoverableException` is thrown.
- `SQLClientInfoException`

A SQLClientInfoException is thrown by the Connection.setClientInfo method when one or more client properties cannot be set. The SQLClientInfoException indicates which properties cannot be set.

BatchUpdateException

A BatchUpdateException object contains the following items about an error that occurs during execution of a batch of SQL statements:

- A String object that contains a description of the error, or null.
- A String object that contains the SQLSTATE for the failing SQL statement, or null
- An integer value that contains the error code, or zero
- An integer array of update counts for SQL statements in the batch, or null
- A pointer to an SQLException object, or null

One BatchUpdateException is thrown for the entire batch. At least one SQLException object is chained to the BatchUpdateException object. The SQLException objects are chained in the same order as the corresponding statements were added to the batch. To help you match SQLException objects to statements in the batch, the error description field for each SQLException object begins with this string:

```
Error for batch element #n:
```

n is the number of the statement in the batch.

SQL warnings during batch execution do not throw BatchUpdateExceptions. To obtain information about warnings, use the Statement.getWarnings method on the object on which you ran the executeBatch method. You can then retrieve an error description, SQLSTATE, and error code for each SQLWarning object.

SQLWarning

The IBM Data Server Driver for JDBC and SQLJ accumulates warnings when SQL statements return positive SQLCODEs, and when SQL statements return 0 SQLCODEs with non-zero SQLSTATEs.

Calling getWarnings retrieves an SQLWarning object.

Important: When a call to Statement.executeUpdate or PreparedStatement.executeUpdate affects no rows, the IBM Data Server Driver for JDBC and SQLJ generates an SQLWarning with error code +100.

When a call to ResultSet.next returns no rows, the IBM Data Server Driver for JDBC and SQLJ does not generate an SQLWarning.

A generic SQLWarning object contains the following information:

- A String object that contains a description of the warning, or null
- A String object that contains the SQLSTATE, or null
- An int value that contains an error code
- A pointer to the next SQLWarning, or null

Under the IBM Data Server Driver for JDBC and SQLJ, like an SQLException object, an SQLWarning object can also contain information specific to Db2. The information specific to Db2, for an SQLWarning object, is the same as the information for an SQLException object.

Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ

As in all Java programs, error handling for JDBC applications is done using `try/catch` blocks. Methods throw exceptions when an error occurs, and the code in the `catch` block handles those exceptions.

Procedure

The basic steps for handling an `SQLException` in a JDBC program that runs under the IBM Data Server Driver for JDBC and SQLJ are:

1. Give the program access to the `com.ibm.db2.jcc.DB2Diagnosable` interface and the `com.ibm.db2.jcc.DB2Sqlca` class.

   You can fully qualify all references to them, or you can import them:

   ```
   import com.ibm.db2.jcc.DB2Diagnosable;
   import com.ibm.db2.jcc.DB2Sqlca;
   ```

2. Optional: During a connection to a data server, set the retrieveMessagesFromServerOnGetMessage property to `true` if you want full message text from an `SQLException.getMessage` call.
3. Optional: During a IBM Data Server Driver for JDBC and SQLJ type 2 connectivity connection to a Db2 for z/OS data source, set the extendedDiagnosticLevel property to `EXTENDED_DIAG_MESSAGE_TEXT` (241) if you want extended diagnostic information similar to the information that is provided by the SQL GET DIAGNOSTICS statement from an `SQLException.getMessage` call.
4. Put code that can generate an `SQLException` in a `try` block.
5. In the `catch` block, perform the following steps in a loop:
   a) Test whether you have retrieved the last `SQLException`. If not, continue to the next step.
   b) Optional: For an SQL statement that executes on an IBM Informix data source, execute the `com.ibm.db2.jcc.DB2Statement.getIDSSQLStatementOffSet` method to determine which columns have syntax errors.

      `DB2Statement.getIDSSQLStatementOffSet` returns the offset into the SQL statement of the first syntax error.

   c) Optional: For an SQL statement that executes on an IBM Informix data source, execute the `SQLException.getCause` method to retrieve any ISAM error messages.

      i) If the `Throwable` that is returned by `SQLException.getCause` is not null, perform one of the following sets of steps:

      - Issue `SQLException.printStackTrace` to print an error message that includes the ISAM error message text. The ISAM error message text is preceded by the string "Caused by:".
      - Retrieve the error code and message text for the ISAM message:

        a) Test whether the `Throwable` is an instance of an `SQLException`. If so, retrieve the SQL error code from that `SQLException`.

        b) Execute the `Throwable.getMessage` method to retrieve the text of the ISAM message.

   d) Check whether any IBM Data Server Driver for JDBC and SQLJ-only information exists by testing whether the `SQLException` is an instance of `DB2Diagnosable`.

      If so:

      i) Cast the object to a `DB2Diagnosable` object.

      ii) Optional: Invoke the `DB2Diagnosable.printTrace` method to write all `SQLException` information to a `java.io.PrintWriter` object.

      iii) Invoke the `DB2Diagnosable.getThrowable` method to determine whether an underlying `java.lang.Throwable` caused the `SQLException`.

      iv) Invoke the `DB2Diagnosable.getSqlca` method to retrieve the DB2Sqlca object.

      v) Invoke the `DB2Sqlca.getSqlCode` method to retrieve an SQL error code value.

vi) Invoke the `DB2Sqlca.getSqlErrmc` method to retrieve a string that contains all SQLERRMC values, or invoke the `DB2Sqlca.getSqlErrmcTokens` method to retrieve the SQLERRMC values in an array.

vii) Invoke the `DB2Sqlca.getSqlErrp` method to retrieve the SQLERRP value.

viii) Invoke the `DB2Sqlca.getSqlErrd` method to retrieve the SQLERRD values in an array.

ix) Invoke the `DB2Sqlca.getSqlWarn` method to retrieve the SQLWARN values in an array.

x) Invoke the `DB2Sqlca.getSqlState` method to retrieve the SQLSTATE value.

xi) Invoke the `DB2Sqlca.getMessage` method to retrieve error message text from the data source.

e) Invoke the `SQLException.getNextException` method to retrieve the next `SQLException`.

Example

The following code demonstrates how to obtain IBM Data Server Driver for JDBC and SQLJ-specific information from an `SQLException` that is provided with the IBM Data Server Driver for JDBC and SQLJ. The numbers to the right of selected statements correspond to the previously-described steps.

Figure 20. Processing an SQLException under the IBM Data Server Driver for JDBC and SQLJ

```
import java.sql.*;                       // Import JDBC API package
import com.ibm.db2.jcc.DB2Diagnosable;  // Import packages for Db2       1
import com.ibm.db2.jcc.DB2Sqlca;        // SQLException support
java.io.PrintWriter printWriter;        // For dumping all SQLException
                                        // information
String url = "jdbc:db2://myhost:9999/myDB:" +                           2
  "retrieveMessagesFromServerOnGetMessage=true;";
                                 // Set properties to retrieve full message
                                 // text
String user = "db2adm";
String password = "db2adm";
java.sql.Connection con =
  java.sql.DriverManager.getConnection (url, user, password)
                                 // Connect to a Db2 for z/OS data source


…
try {                                                                   4
  // Code that could generate SQLExceptions
 …
} catch(SQLException sqle) {
    while(sqle != null) {            // Check whether there are more   5a
                                     // SQLExceptions to process
 //=====> Optional IBM Data Server Driver for JDBC and SQLJ-only
 // error processing
      if (sqle instanceof DB2Diagnosable) {                             5d
      // Check if IBM Data Server Driver for JDBC and SQLJ-only
      // information exists
          com.ibm.db2.jcc.DB2Diagnosable diagnosable =
            (com.ibm.db2.jcc.DB2Diagnosable)sqle;                       5d1
          diagnosable.printTrace (printWriter, "");                     5d2
          java.lang.Throwable throwable =
            diagnosable.getThrowable();                                 5d3
          if (throwable != null) {
            // Extract java.lang.Throwable information
            // such as message or stack trace.
            …
          }
          DB2Sqlca sqlca = diagnosable.getSqlca();                      5d4
                                       // Get DB2Sqlca object
          if (sqlca != null) {         // Check that DB2Sqlca is not null
            int sqlCode = sqlca.getSqlCode(); // Get the SQL error code 5d5
            String sqlErrmc = sqlca.getSqlErrmc();                      5d6
                                       // Get the entire SQLERRMC
            String[] sqlErrmcTokens = sqlca.getSqlErrmcTokens();
                                       // You can also retrieve the
                                       // individual SQLERRMC tokens
            String sqlErrp = sqlca.getSqlErrp();                        5d7
                                       // Get the SQLERRP
            int[] sqlErrd = sqlca.getSqlErrd();                         5d8
                                       // Get SQLERRD fields
            char[] sqlWarn = sqlca.getSqlWarn();                        5d9
```

```
                                        // Get SQLWARN fields
            String sqlState = sqlca.getSqlState();                      5d10
                                        // Get SQLSTATE
            String errMessage = sqlca.getMessage();                     5d11
                                        // Get error message

            System.err.println ("Server error message: " + errMessage);

            System.err.println ("---------------- SQLCA ----------------");
            System.err.println ("Error code: " + sqlCode);
            System.err.println ("SQLERRMC: " + sqlErrmc);
            If (sqlErrmcTokens != null) {
              for (int i=0; i< sqlErrmcTokens.length; i++) {
                System.err.println ("  token " + i + ": " + sqlErrmcTokens[i]);
              }
            }
            System.err.println ( "SQLERRP: " + sqlErrp );
            System.err.println (
              "SQLERRD(1): " + sqlErrd[0] + "\n" +
              "SQLERRD(2): " + sqlErrd[1] + "\n" +
              "SQLERRD(3): " + sqlErrd[2] + "\n" +
              "SQLERRD(4): " + sqlErrd[3] + "\n" +
              "SQLERRD(5): " + sqlErrd[4] + "\n" +
              "SQLERRD(6): " + sqlErrd[5] );
            System.err.println (
              "SQLWARN1: " + sqlWarn[0] + "\n" +
              "SQLWARN2: " + sqlWarn[1] + "\n" +
              "SQLWARN3: " + sqlWarn[2] + "\n" +
              "SQLWARN4: " + sqlWarn[3] + "\n" +
              "SQLWARN5: " + sqlWarn[4] + "\n" +
              "SQLWARN6: " + sqlWarn[5] + "\n" +
              "SQLWARN7: " + sqlWarn[6] + "\n" +
              "SQLWARN8: " + sqlWarn[7] + "\n" +
              "SQLWARN9: " + sqlWarn[8] + "\n" +
              "SQLWARNA: " + sqlWarn[9] );
            System.err.println ("SQLSTATE: " + sqlState);
                                        // portion of SQLException
          }
        sqle=sqle.getNextException();     // Retrieve next SQLException      5e
      }
}
```

Related tasks

“Handling an SQLWarning under the IBM Data Server Driver for JDBC and SQLJ” on page 113
Unlike SQL errors, SQL warnings do not cause JDBC methods to throw exceptions. Instead, the `Connection`, `Statement`, `PreparedStatement`, `CallableStatement`, and `ResultSet` classes contain `getWarnings` methods, which you need to invoke after you execute SQL statements to determine whether any SQL warnings were generated.

“Handling SQL warnings in an SQLJ application” on page 173
Other than a +100 SQL error code on a SELECT INTO statement, warnings from the data server do not throw SQLExceptions. To handle warnings from the data server, you need to give the program access to the `java.sql.SQLWarning` class.

“Handling SQL errors in an SQLJ application” on page 172
SQLJ clauses use the JDBC class `java.sql.SQLException` for error handling.

Related reference

“Error codes issued by the IBM Data Server Driver for JDBC and SQLJ” on page 503
Warning codes in the ranges +4200 to +4299, and +4450 to +4499, and error codes in the ranges -4200 to -4299, and -4450 to -4499 are reserved for the IBM Data Server Driver for JDBC and SQLJ.

Handling an SQLWarning under the IBM Data Server Driver for JDBC and SQLJ

Unlike SQL errors, SQL warnings do not cause JDBC methods to throw exceptions. Instead, the `Connection`, `Statement`, `PreparedStatement`, `CallableStatement`, and `ResultSet` classes

contain getWarnings methods, which you need to invoke after you execute SQL statements to determine whether any SQL warnings were generated.

Procedure

The basic steps for retrieving SQL warning information are:

1. Optional: During connection to the database server, set properties that affect SQLWarning objects.

   If you want full message text from a data server when you execute SQLWarning.getMessage calls, set the retrieveMessagesFromServerOnGetMessage property to true.

   If you are using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to a Db2 for z/OS data source, and you want extended diagnostic information that is similar to the information that is provided by the SQL GET DIAGNOSTICS statement when you execute SQLWarning.getMessage calls, set the extendedDiagnosticLevel property to EXTENDED_DIAG_MESSAGE_TEXT (241).
2. Immediately after invoking a method that connects to a database server or executes an SQL statement, invoke the getWarnings method to retrieve an SQLWarning object.
3. Perform the following steps in a loop:
   a) Test whether the SQLWarning object is null. If not, continue to the next step.
   b) Invoke the SQLWarning.getMessage method to retrieve the warning description.
   c) Invoke the SQLWarning.getSQLState method to retrieve the SQLSTATE value.
   d) Invoke the SQLWarning.getErrorCode method to retrieve the error code value.
   e) If you want specific warning information in Db2, perform the same steps that you perform to get specific information for an SQLException in Db2.
   f) Invoke the SQLWarning.getNextWarning method to retrieve the next SQLWarning.

Example

The following code illustrates how to obtain generic SQLWarning information. The numbers to the right of selected statements correspond to the previously-described steps.

```
String url = "jdbc:db2://myhost:9999/myDB:" +                          1
  "retrieveMessagesFromServerOnGetMessage=true;";
                                  // Set properties to retrieve full message
                                  // text
String user = "db2adm";
String password = "db2adm";
java.sql.Connection con =
  java.sql.DriverManager.getConnection (url, user, password)
                                  // Connect to a Db2
for z/OS data source

Statement stmt;
ResultSet rs;
SQLWarning sqlwarn;
…
stmt = con.createStatement();     // Create a Statement object
rs = stmt.executeQuery("SELECT * FROM EMPLOYEE");
                                  // Get the result table from the query
sqlwarn = stmt.getWarnings();     // Get any warnings generated           2
while (sqlwarn != null) {         // While there are warnings, get and    3a
                                  // print warning information
  System.out.println ("Warning description: " + sqlwarn.getMessage());   3b
  System.out.println ("SQLSTATE: " + sqlwarn.getSQLState());             3c
  System.out.println ("Error code: " + sqlwarn.getErrorCode());         3d
  sqlwarn=sqlwarn.getNextWarning();     // Get next SQLWarning           3f
}
```

Figure 21. Example of processing an SQLWarning

Retrieving information from a BatchUpdateException

When an error occurs during execution of a statement in a batch, processing continues. However, `executeBatch` throws a `BatchUpdateException`.

Procedure

To retrieve information from the `BatchUpdateException`, follow these steps:

1. Use the `BatchUpdateException.getUpdateCounts` method to determine the number of rows that each SQL statement in the batch updated before the exception was thrown.

   `getUpdateCount` returns an array with an element for each statement in the batch. An element has one of the following values:

   n
   The number of rows that the statement updated.

   Statement.SUCCESS_NO_INFO
   This value is returned if the number of updated rows cannot be determined. The number of updated rows cannot be determined if the following conditions are true:

   - The application is connected to a subsystem that is in Db2 for z/OS Version 8 new-function mode, or later.
   - The application is using Version 3.1 or later of the IBM Data Server Driver for JDBC and SQLJ.
   - The IBM Data Server Driver for JDBC and SQLJ uses multi-row INSERT operations to execute batch updates.

   Statement.EXECUTE_FAILED
   This value is returned if the statement did not execute successfully.
2. If the batched statement can return automatically generated keys:
   a) Cast the `BatchUpdateException` to a `com.ibm.db2.jcc.DBBatchUpdateException`.
   b) Call the `DBBatchUpdateException.getDBGeneratedKeys` method to retrieve an array of `ResultSet` objects that contains the automatically generated keys for each execution of the batched SQL statement.
   c) Test whether each `ResultSet` in the array is null.

   Each `ResultSet` contains:

   - If the `ResultSet` is not null, it contains the automatically generated keys for an execution of the batched SQL statement.
   - If the `ResultSet` is null, execution of the batched statement failed.
3. Use `SQLException` methods `getMessage`, `getSQLState`, and `getErrorCode` to retrieve the description of the error, the SQLSTATE, and the error code for the first error.
4. Use the `BatchUpdateException.getNextException` method to get a chained `SQLException`.
5. In a loop, execute the `getMessage`, `getSQLState`, `getErrorCode`, and `getNextException` method calls to obtain information about an `SQLException` and get the next `SQLException`.

Example

The following code fragment demonstrates how to obtain the fields of a `BatchUpdateException` and the chained `SQLException` objects for a batched statement that returns automatically generated keys. The example assumes that there is only one column in the automatically generated key, and that there is always exactly one key value, whose data type is numeric. The numbers to the right of selected statements correspond to the previously-described steps.

```
try {
  // Batch updates
} catch(BatchUpdateException buex) {
    System.err.println("Contents of BatchUpdateException:");
    System.err.println(" Update counts: ");
```

```
    int [] updateCounts = buex.getUpdateCounts();              1
    for (int i = 0; i < updateCounts.length; i++) {
      System.err.println("  Statement " + i + ":" + updateCounts[i]);
    }
    ResultSet[] resultList =
      ((DBBatchUpdateException)buex).getDBGeneratedKeys();     2
    for (i = 0; i < resultList.length; i++)
    {
      if (resultList[i] == null)
         continue; // Skip the ResultSet for which there was a failure
      else {
        rs.next();
        java.math.BigDecimal idColVar = rs.getBigDecimal(1);
                                      // Get automatically generated key
                                      // value
        System.out.println("Automatically generated key value = " + idColVar);
      }
    }
    System.err.println(" Message: " + buex.getMessage());      3
    System.err.println(" SQLSTATE: " + buex.getSQLState());
    System.err.println(" Error code: " + buex.getErrorCode());
    SQLException ex = buex.getNextException();                 4
    while (ex != null) {                                       5
      System.err.println("SQL exception:");
      System.err.println(" Message: " + ex.getMessage());
      System.err.println(" SQLSTATE: " + ex.getSQLState());
      System.err.println(" Error code: " + ex.getErrorCode());
      ex = ex.getNextException();
    }
}
```

Related tasks

“Making batch updates in JDBC applications” on page 33
With batch updates, instead of updating rows of a table one at a time, you can direct JDBC to execute a group of updates at the same time. Statements that can be included in the same batch of updates are known as *batchable* statements.

Memory use for IBM Data Server Driver for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS

In general, applications that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity require more memory than applications that use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

With IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, an application receives data from the Db2 database server in network packets, and receives only the data that is contained in a particular row and column of a table.

Applications that run under IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS generally require more memory. IBM Data Server Driver for JDBC and SQLJ type 2 connectivity has a direct, native interface to Db2 for z/OS. For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, the driver must provide memory in which Db2 for z/OS writes data. Because the amount of data that is needed can vary from row to row, and the driver has no information about how much memory is needed for each row, the driver must allocate the maximum amount of memory that any row might need. This value is determined from DESCRIBE information on the SELECT statement that generates the result table. For example, when an application that uses IBM Data Server Driver for JDBC and SQLJ type 2 connectivity selects a column that is defined as VARCHAR(32000), the driver must allocate 32000 bytes for each row of the result table.

The extra memory requirements can be particularly great for retrieval of LOB columns, which can be defined with lengths of up to 2 GB, or for CAST expressions that cast values to LOB types with large length attributes.

In general, even when you use a 64-bit JVM, all native connectivity to Db2 for z/OS is below the bar, with 32-bit addressing limits. Although the maximum size of any row is defined as approximately 2 GB, the practical maximum amount of available memory for use by IBM Data Server Driver for JDBC and SQLJ type 2 connectivity is generally significantly less. However, if the IBM Data Server Driver for JDBC and SQLJ can use limited block fetch to retrieve the data for a query or for a stored procedure result set, the data can be passed to the driver using full 64-bit addressing.

Two ways to alleviate excess memory use for LOB retrieval and manipulation are to use progressive streaming or LOB locators. You enable progressive streaming or LOB locator use by setting the progressiveStreaming property or the fullyMaterializeLobData property.

Related concepts

"LOBs in JDBC applications with the IBM Data Server Driver for JDBC and SQLJ" on page 56
The IBM Data Server Driver for JDBC and SQLJ supports methods for updating and retrieving data from BLOB, CLOB, and DBCLOB columns in a table, and for calling stored procedures or user-defined functions with BLOB or CLOB parameters.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

Disconnecting from data sources in JDBC applications

When you have finished with a connection to a data source, it is *essential* that you close the connection to the data source. Doing this releases the `Connection` object's database and JDBC resources immediately.

Procedure

To close the connection to the data source, use the `close` method.

For example:

```
 Connection con;
 …
con.close();
```

For a connection to a Db2 data source, if autocommit mode is not on, the connection needs to be on a unit-of-work boundary before you close the connection.

For a connection to an IBM Informix database, if the database supports logging, and autocommit mode is not on, the connection needs to be on a unit-of-work boundary before you close the connection.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, when you close the connection to a data source, the driver issues an implicit rollback to ensure consistency of the underlying RRSAF thread before thread termination.

Related concepts

"How JDBC applications connect to a data source" on page 11
Before you can execute SQL statements in any SQL program, you must be connected to a data source.

Chapter 4. SQLJ application programming

Writing an SQLJ application has much in common with writing an SQL application in any other language.

In general, you need to do the following things:

- Import the Java packages that contain SQLJ and JDBC methods.
- Declare variables for sending data to or retrieving data from data server tables.
- Connect to a data source.
- Execute SQL statements.
- Handle SQL errors and warnings.
- Disconnect from the data source.

Although the tasks that you need to perform are similar to those in other languages, the way that you execute those tasks, and the order in which you execute those tasks, is somewhat different.

Example of a simple SQLJ application

A simple SQLJ application demonstrates the basic elements that JDBC applications need to include.

Figure 22. Simple SQLJ application

```
import sqlj.runtime.*;                                          1
import java.sql.*;

#sql context EzSqljCtx;                                         3a
#sql iterator EzSqljNameIter (String LASTNAME);                 4a

public class EzSqlj {
 public static void main(String args[])
    throws SQLException
 {
    EzSqljCtx ctx = null;
    String URLprefix = "jdbc:db2:";
    String url;
    url = new String(URLprefix + args[0]);
                                        // Location name is an input parameter
    String hvmgr="000010";                                      2
    String hvdeptno="A00";
    try {                                                       3b
      Class.forName("com.ibm.db2.jcc.DB2Driver");
    } catch (Exception e)
    {
       throw new SQLException("Error in EzSqlj: Could not load the driver");
    }
    try
    {
       System.out.println("About to connect using url: " + url);
       Connection con0 = DriverManager.getConnection(url);      3c
                                        // Create a JDBC Connection
       con0.setAutoCommit(false);       // set autocommit OFF
       ctx = new EzSqljCtx(con0);                               3d

       try
       {
         EzSqljNameIter iter;
         int count=0;

         #sql [ctx] iter =
           {SELECT LASTNAME FROM EMPLOYEE};                     4b
                                        // Create result table of the SELECT
         while (iter.next()) {                                  4c
            System.out.println(iter.LASTNAME());
                                        // Retrieve rows from result table
            count++;
         }
         System.out.println("Retrieved " + count + " rows of data");
         iter.close();                  // Close the iterator
       }
```

© Copyright IBM Corp. 1998, 2017

```
       catch( SQLException e )                                          5
       {
          System.out.println ("**** SELECT SQLException...");
          while(e!=null) {
            System.out.println ("Error msg: " + e.getMessage());
            System.out.println ("SQLSTATE: " + e.getSQLState());
            System.out.println ("Error code: " + e.getErrorCode());
            e = e.getNextException(); // Check for chained exceptions
          }
       }
       catch( Exception e )
       {
          System.out.println("**** NON-SQL exception   = " + e);
          e.printStackTrace();
       }
       try
       {
         #sql [ctx]                                                     4d
           {UPDATE DEPARTMENT SET MGRNO=:hvmgr
              WHERE DEPTNO=:hvdeptno};   // Update data for one
department
                                                                        6
         #sql [ctx] {COMMIT};            // Commit the update
       }
       catch( SQLException e )
       {
          System.out.println ("**** UPDATE SQLException...");
          System.out.println ("Error msg: " + e.getMessage() + ". SQLSTATE=" +
            e.getSQLState() + " Error code=" + e.getErrorCode());
          e.printStackTrace();
       }
       catch( Exception e )
       {
          System.out.println("**** NON-SQL exception   = " + e);
          e.printStackTrace();
       }
       ctx.close();                                                     7
  }
  catch(SQLException e)
  {
     System.out.println ("**** SQLException ...");
     System.out.println ("Error msg: " + e.getMessage() + ". SQLSTATE=" +
       e.getSQLState() + " Error code=" + e.getErrorCode());
     e.printStackTrace();
  }
  catch(Exception e)
  {
    System.out.println ("**** NON-SQL exception = " + e);
    e.printStackTrace();
  }
 }
}
```

Notes to Figure 22 on page 119:

Note	Description
1	These statements import the `java.sql` package, which contains the JDBC core API, and the `sqlj.runtime` package, which contains the SQLJ API. For information on other packages or classes that you might need to access, see "Java packages for SQLJ support".
2	`String` variables hvmgr and hvdeptno are *host identifiers*, which are equivalent to host variables. See "Variables in SQLJ applications" for more information.
3a, 3b, 3c, and 3d	These statements demonstrate how to connect to a data source using one of the three available techniques. See "Connecting to a data source using SQLJ" for more details. Step 3b (loading the JDBC driver) is not necessary if you use JDBC 4.0 or later.
4a , 4b, 4c, and 4d	These statements demonstrate how to execute SQL statements in SQLJ. Statement 4a demonstrates the SQLJ equivalent of declaring an SQL cursor. Statements 4b and 4c show one way of doing the SQLJ equivalent of executing an SQL OPEN CURSOR and SQL FETCHes. Statement 4d shows how to do the SQLJ equivalent of performing an SQL UPDATE. For more information, see "SQL statements in an SQLJ application".

Note	Description
5	This `try/catch` block demonstrates the use of the `SQLException` class for SQL error handling. For more information on handling SQL errors, see "Handling SQL errors in an SQLJ application". For more information on handling SQL warnings, see "Handling SQL warnings in an SQLJ application".
6	This is an example of a comment. For rules on including comments in SQLJ programs, see "Comments in an SQLJ application".
7	This statement closes the connection to the data source. See "Closing the connection to the data source in an SQLJ application".

Connecting to a data source using SQLJ

In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

About this task

You can use one of six techniques to connect to a data source in an SQLJ program. Two use the JDBC `DriverManager` interface, two use the JDBC `DataSource` interface, one uses a previously created connection context, and one uses the default connection.

Related concepts

"How JDBC applications connect to a data source" on page 11
Before you can execute SQL statements in any SQL program, you must be connected to a data source.

SQLJ connection technique 1: JDBC DriverManager interface

SQLJ connection technique 1 uses the JDBC `DriverManager` interface as the underlying means for creating the connection.

Procedure

To use SQLJ connection technique 1, follow these steps:

1. Execute an SQLJ *connection declaration clause*.

   Doing this generates a *connection context class*. The simplest form of the connection declaration clause is:

   ```
   #sql context context-class-name;
   ```

   The name of the generated connection context class is *context-class-name*.
2. Load a JDBC driver by invoking the `Class.forName` method.
   - Invoke `Class.forName` this way:

     ```
     Class.forName("com.ibm.db2.jcc.DB2Driver");
     ```

     This step is unnecessary if you use the JDBC 4.0 driver or later.
3. Invoke the constructor for the connection context class that you created in step "1" on page 121.

   Doing this creates a connection context object that you specify in each SQL statement that you execute at the associated data source. The constructor invocation statement needs to be in one of the following forms:

   ```
   connection-context-class connection-context-object=
     new connection-context-class(String url, boolean autocommit);

   connection-context-class connection-context-object=
     new connection-context-class(String url, String user,
   ```

```
    String password, boolean autocommit);
connection-context-class connection-context-object=
  new connection-context-class(String url, Properties info,
    boolean autocommit);
```

The meanings of the parameters are:

url
A string that specifies the location name that is associated with the data source. That argument has one of the forms that are specified in "Connect to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ". The form depends on which JDBC driver you are using.

user* and *password
Specify a user ID and password for connection to the data source, if the data source to which you are connecting requires them.

If the data source is a Db2 for z/OS system, and you do not specify these parameters, Db2 uses the external security environment, such as the RACF security environment, that was previously established for the user. For a CICS connection, you cannot specify a user ID or password.

info
Specifies an object of type `java.util.Properties` that contains a set of driver properties for the connection. For the IBM Data Server Driver for JDBC and SQLJ, you can specify any of the properties listed in "Properties for the IBM Data Server Driver for JDBC and SQLJ".

autocommit
Specifies whether you want the database manager to issue a COMMIT after every statement. Possible values are `true` or `false`. If you specify `false`, you need to do explicit commit operations.

Example

The following code uses connection technique 1 to create a connection to location NEWYORK. The connection requires a user ID and password, and does not require autocommit. The numbers to the right of selected statements correspond to the previously-described steps.

```
#sql context Ctx;             // Create connection context class Ctx       1
String userid="dbadm";        // Declare variables for user ID and password
String password="dbadm";
String empname;               // Declare a host variable
…
try {                         // Load the JDBC driver
  Class.forName("com.ibm.db2.jcc.DB2Driver");                             2
}
catch (ClassNotFoundException e) {
   e.printStackTrace();
}
Ctx myConnCtx=                                                            3
  new Ctx("jdbc:db2://sysmvs1.stl.ibm.com:5021/NEWYORK",
  userid,password,false);     // Create connection context object myConnCtx
                              // for the connection to NEWYORK
#sql [myConnCtx] {SELECT LASTNAME INTO :empname FROM EMPLOYEE
   WHERE EMPNO='000010'};
                              // Use myConnCtx for executing an SQL statement
```

Figure 23. Using connection technique 1 to connect to a data source

SQLJ connection technique 2: JDBC DriverManager interface

SQLJ connection technique 2 uses the JDBC `DriverManager` interface as the underlying means for creating the connection.

Procedure

To use SQLJ connection technique 2, follow these steps:

1. Execute an SQLJ *connection declaration clause*.

Doing this generates a *connection context class*. The simplest form of the connection declaration clause is:

```
#sql context context-class-name;
```

The name of the generated connection context class is *context-class-name*.

2. Load a JDBC driver by invoking the `Class.forName` method.

   - Invoke `Class.forName` this way:

     ```
     Class.forName("com.ibm.db2.jcc.DB2Driver");
     ```

   This step is unnecessary if you use the JDBC 4.0 driver or later.

3. Invoke the JDBC `DriverManager.getConnection` method.

   Doing this creates a JDBC connection object for the connection to the data source. You can use any of the forms of `getConnection` that are specified in "Connect to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ".

   The meanings of the *url*, *user*, and *password* parameters are:

   url
   A string that specifies the location name that is associated with the data source. That argument has one of the forms that are specified in "Connect to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ". The form depends on which JDBC driver you are using.

   user* and *password
   Specify a user ID and password for connection to the data source, if the data source to which you are connecting requires them.

   If the data source is a Db2 for z/OS system, and you do not specify these parameters, Db2 uses the external security environment, such as the RACF security environment, that was previously established for the user. For a CICS connection, you cannot specify a user ID or password.

4. Invoke the constructor for the connection context class that you created in step “1” on page 122

   Doing this creates a connection context object that you specify in each SQL statement that you execute at the associated data source. The constructor invocation statement needs to be in the following form:

   ```
   connection-context-class connection-context-object=
     new connection-context-class(Connection JDBC-connection-object);
   ```

   The *JDBC-connection-object* parameter is the `Connection` object that you created in step “3” on page 123.

Example

The following code uses connection technique 2 to create a connection to location NEWYORK. The connection requires a user ID and password, and does not require autocommit. The numbers to the right of selected statements correspond to the previously-described steps.

```
#sql context Ctx;           // Create connection context class Ctx       1
String userid="dbadm";      // Declare variables for user ID and password
String password="dbadm";
String empname;             // Declare a host variable
…
try {                       // Load the JDBC driver
  Class.forName("com.ibm.db2.jcc.DB2Driver");                           2
}
catch (ClassNotFoundException e) {
   e.printStackTrace();
}
Connection jdbccon=                                                     3
  DriverManager.getConnection("jdbc:db2://sysmvs1.stl.ibm.com:5021/NEWYORK",
    userid,password);
                            // Create JDBC connection object jdbccon
jdbccon.setAutoCommit(false); // Do not autocommit
Ctx myConnCtx=new Ctx(jdbccon);                                         4
                            // Create connection context object myConnCtx
                            // for the connection to NEWYORK
#sql [myConnCtx] {SELECT LASTNAME INTO :empname FROM EMPLOYEE
   WHERE EMPNO='000010'};
                            // Use myConnCtx for executing an SQL statement
```

Figure 24. Using connection technique 2 to connect to a data source

SQLJ connection technique 3: JDBC DataSource interface

SQLJ connection technique 3 uses the JDBC `DataSource` as the underlying means for creating the connection.

Procedure

To use SQLJ connection technique 3, follow these steps:

1. Execute an SQLJ *connection declaration clause*.

   Doing this generates a *connection context class*. The simplest form of the connection declaration clause is:

   ```
   #sql context context-class-name;
   ```

   The name of the generated connection context class is *context-class-name*.
2. If your system administrator created a `DataSource` object in a different program, follow these steps. Otherwise, create a `DataSource` object and assign properties to it.
   a) Obtain the logical name of the data source to which you need to connect.
   b) Create a context to use in the next step.
   c) In your application program, use the Java Naming and Directory Interface (JNDI) to get the `DataSource` object that is associated with the logical data source name.
3. Invoke the JDBC `DataSource.getConnection` method.

   Doing this creates a JDBC connection object for the connection to the data source. You can use one of the following forms of `getConnection`:

   ```
   getConnection();
   getConnection(user, password);
   ```

   The meanings of the *user* and *password* parameters are:

   user* and *password
   Specify a user ID and password for connection to the data source, if the data source to which you are connecting requires them.

   If the data source is a Db2 for z/OS system, and you do not specify these parameters, Db2 uses the external security environment, such as the RACF security environment, that was previously established for the user. For a CICS connection, you cannot specify a user ID or password.

4. If the default autocommit mode is not appropriate, invoke the JDBC `Connection.setAutoCommit` method.

   Doing this indicates whether you want the database manager to issue a COMMIT after every statement. The form of this method is:

   ```
   setAutoCommit(boolean autocommit);
   ```

   For environments other than the environments for CICS, stored procedures, and user-defined functions, the default autocommit mode for a JDBC connection is `true`. To disable autocommit, invoke `setAutoCommit(false)`.
5. Invoke the constructor for the connection context class that you created in step "1" on page 124.

   Doing this creates a connection context object that you specify in each SQL statement that you execute at the associated data source. The constructor invocation statement needs to be in the following form:

   ```
   connection-context-class connection-context-object=
     new connection-context-class(Connection JDBC-connection-object);
   ```

   The *JDBC-connection-object* parameter is the `Connection` object that you created in step "3" on page 124.

Example

The following code uses connection technique 3 to create a connection to a location with logical name `jdbc/sampledb`. This example assumes that the system administrator created and deployed a `DataSource` object that is available through JNDI lookup. The numbers to the right of selected statements correspond to the previously-described steps.

```
import java.sql.*;
import javax.naming.*;
import javax.sql.*;
…
#sql context CtxSqlj;       // Create connection context class CtxSqlj   1
Context ctx=new InitialContext();                                        2b
DataSource ds=(DataSource)ctx.lookup("jdbc/sampledb");                   2c
Connection con=ds.getConnection();                                       3
String empname;             // Declare a host variable
…
con.setAutoCommit(false);   // Do not autocommit                         4
CtxSqlj myConnCtx=new CtxSqlj(con);                                      5
                            // Create connection context object myConnCtx
#sql [myConnCtx] {SELECT LASTNAME INTO :empname FROM EMPLOYEE
   WHERE EMPNO='000010'};
                            // Use myConnCtx for executing an SQL statement
```

Figure 25. Using connection technique 3 to connect to a data source

SQLJ connection technique 4: JDBC DataSource interface

SQLJ connection technique 4 uses the JDBC `DataSource` as the underlying means for creating the connection. This technique **requires** that the `DataSource` is registered with JNDI.

Procedure

To use SQLJ connection technique 4, follow these steps:

1. From your system administrator, obtain the logical name of the data source to which you need to connect.
2. Execute an SQLJ connection declaration clause.

   For this type of connection, the connection declaration clause needs to be of this form:

   ```
   #sql public static context context-class-name
    with (dataSource="logical-name");
   ```

The connection context must be declared as public and static. *logical-name* is the data source name that you obtained in step "1" on page 125.

3. Invoke the constructor for the connection context class that you created in step "2" on page 125.

   Doing this creates a connection context object that you specify in each SQL statement that you execute at the associated data source. The constructor invocation statement needs to be in one of the following forms:

```
connection-context-class connection-context-object=
  new connection-context-class();

connection-context-class connection-context-object=
  new connection-context-class (String user,
    String password);
```

   The meanings of the *user* and *password* parameters are:

   user* and *password
   Specify a user ID and password for connection to the data source, if the data source to which you are connecting requires them.

   If the data source is a Db2 for z/OS system, and you do not specify these parameters, Db2 uses the external security environment, such as the RACF security environment, that was previously established for the user. For a CICS connection, you cannot specify a user ID or password.

Example

The following code uses connection technique 4 to create a connection to a location with logical name `jdbc/sampledb`. The connection requires a user ID and password.

```
#sql public static context Ctx
  with (dataSource="jdbc/sampledb");                                    2
                                // Create connection context class Ctx
String userid="dbadm";          // Declare variables for user ID and password
String password="dbadm";

String empname;                 // Declare a host variable
…
Ctx myConnCtx=new Ctx(userid, password);                                3
                                // Create connection context object myConnCtx
                                // for the connection to jdbc/sampledb
#sql [myConnCtx] {SELECT LASTNAME INTO :empname FROM EMPLOYEE
   WHERE EMPNO='000010'};
                                // Use myConnCtx for executing an SQL statement
```

Figure 26. Using connection technique 4 to connect to a data source

SQLJ connection technique 5: Use a previously created connection context

SQLJ connection technique 5 uses a previously created connection context to connect to the data source.

About this task

In general, one program declares a connection context class, creates connection contexts, and passes them as parameters to other programs. A program that uses the connection context invokes a constructor with the passed connection context object as its argument.

Example

Program CtxGen.sqlj declares connection context Ctx and creates instance oldCtx:

```
#sql context Ctx;
…
// Create connection context object oldCtx
```

Program test.sqlj receives oldCtx as a parameter and uses oldCtx as the argument of its connection context constructor:

```
void useContext(sqlj.runtime.ConnectionContext oldCtx)
                                    // oldCtx was created in CtxGen.sqlj
{
  Ctx myConnCtx=
    new Ctx(oldCtx);                // Create connection context object myConnCtx
                                    // from oldCtx
  #sql [myConnCtx] {SELECT LASTNAME INTO :empname FROM EMPLOYEE
     WHERE EMPNO='000010'};
                                    // Use myConnCtx for executing an SQL statement
…
}
```

SQLJ connection technique 6: Use the default connection

SQLJ connection technique 6 uses the default connection to connect to the data source. It should be used only in situations where the database thread is controlled by another resource manager, such as the Java stored procedure environment.

About this task

You use the default connection by specifying your SQL statements without a connection context object. When you use this technique, you do not need to load a JDBC driver unless you explicitly use JDBC interfaces in your program.

The default connection context can be:

- The connection context that is associated with the data source that is bound to the logical name jdbc/defaultDataSource
- An explicitly created connection context that has been set as the default connection context with the `ConnectionContext.setDefaultContext` method. This method of creating a default connection context is not recommended.

In a stored procedure that runs on Db2 for z/OS, or for a CICS or IMS application, when you use the default connection, Db2 for z/OS uses the implicit connection.

Example

The following SQLJ execution clause does not have a connection context, so it uses the default connection context.

```
#sql {SELECT LASTNAME INTO :empname FROM EMPLOYEE
   WHERE EMPNO='000010'};  // Use default connection for
                           // executing an SQL statement
```

Java packages for SQLJ support

Before you can execute SQLJ statements or invoke JDBC methods in your SQLJ program, you need to be able to access all or parts of various Java packages that contain support for those statements.

You can do that either by importing the packages or specific classes, or by using fully-qualified class names. You might need the following packages or classes for your SQLJ program:

sqlj.runtime
Contains the SQLJ run-time API.

java.sql
Contains the core JDBC API.

com.ibm.db2.jcc
Contains the driver-specific implementation of JDBC and SQLJ.

javax.naming
Contains methods for performing Java Naming and Directory Interface (JNDI) lookup.

javax.sql
Contains methods for creating `DataSource` objects.

Variables in SQLJ applications

In application programs in other languages, you use host variables to pass data between the application program and the data server. In SQLJ programs, In SQLJ programs, you can use host variables or *host expressions*.

A host expression begins with a colon (:). The colon is followed by an optional parameter mode identifier (IN, OUT, or INOUT), which is followed by a parenthesized expression clause.

Host variables and host expressions are case sensitive.

A complex expression is an array element or Java expression that evaluates to a single value. A complex expression in an SQLJ clause must be surrounded by parentheses.

Restrictions on variable names: Two strings have special meanings in SQLJ programs. Observe the following restrictions when you use these strings in your SQLJ programs:

- The string __sJT_ is a reserved prefix for variable names that are generated by SQLJ. Do not begin the following types of names with __sJT_:
  - Host expression names
  - Java variable names that are declared in blocks that include executable SQL statements
  - Names of parameters for methods that contain executable SQL statements
  - Names of fields in classes that contain executable SQL statements, or in classes with subclasses or enclosed classes that contain executable SQL statements
- The string _SJ is a reserved suffix for resource files and classes that are generated by SQLJ. Avoid using the string _SJ in class names and input source file names.

Examples

Example: Declaring a Java identifier and using it in a SELECT statement:

In this example, the statement that begins with `#sql` has the same function as a SELECT statement in other languages. This statement assigns the last name of the employee with employee number 000010 to Java identifier `empname`.

```
String empname;
…
#sql [ctxt]
  {SELECT LASTNAME INTO :empname FROM EMPLOYEE WHERE EMPNO='000010'};
```

Example: Declaring a Java identifier and using it in a stored procedure call:

In this example, the statement that begins with `#sql` has the same function as an SQL CALL statement in other languages. This statement uses Java identifier `empno` as an input parameter to stored procedure A. The keyword `IN`, which precedes `empno`, specifies that `empno` is an input parameter. For a parameter in a CALL statement, `IN` is the default. The explicit or default qualifier that indicates how the parameter is used (IN, OUT, or INOUT) must match the corresponding value in the parameter definition that you specified in the CREATE PROCEDURE statement for the stored procedure.

```
String empno = "0000010";
…
#sql [ctxt] {CALL A (:IN empno)};
```

Example: Using a complex expression as a host identifier:

This example uses complex expression (((int)yearsEmployed++/5)*500) as a host expression.

```
#sql [ctxt] {UPDATE EMPLOYEE
        SET BONUS=:(((int)yearsEmployed++/5)*500) WHERE EMPNO=:empID};
```

SQLJ performs the following actions when it processes a complex host expression:

- Evaluates each of the host expressions in the statement, from left to right, before assigning their respective values to the database.
- Evaluates side effects, such as operations with postfix operators, according to normal Java rules. All host expressions are fully evaluated before any of their values are passed to the data server.
- Uses Java rules for rounding and truncation.

Therefore, if the value of yearsEmployed is 6 before the UPDATE statement is executed, the value that is assigned to column BONUS by the UPDATE statement is ((int)6/5)*500, or 500. After 500 is assigned to BONUS, the value of yearsEmployed is incremented.

Indicator variables in SQLJ applications

In SQLJ programs, you can use indicator variables to pass the NULL value to or from a data server, to pass the default value for a column to the data server, or to indicate that a host variable value is unassigned.

A host variable or host expression can be followed by an indicator variable. An indicator variable begins with a colon (:) and has the data type short. For input, an indicator variable indicates whether the corresponding host variable or host expression has the default value, a non-null value, the null value, or is unassigned. An unassigned variable in an SQL statement yields the same results as if the variable and its target column were not in the SQL statement. For output, the indicator variable indicates where the corresponding host variable or host expression has a non-null value or a null value.

In SQLJ programs, indicator variables that indicate a null value perform the same function as assigning the Java null value to a table column. However, you need to use an indicator variable to retrieve the SQL NULL value from a table into a host variable.

You can use indicator variables that assign the default value or the unassigned value to columns to simplify the coding in your applications. For example, if a table has four columns, and you might need to update any combination of those columns, without the use of default indicator variables or unassigned indicator variables, you need 15 UPDATE statements to perform all possible combinations of updates. With default indicator variables and unassigned indicator variables, you can use one UPDATE statement with all four columns in the SET statement to perform all possible updates. You use the indicator variables to indicate which columns you want to set to their default values, and which columns you do not want to update.

For input, SQLJ supports the use of indicator variables for INSERT, UPDATE, or MERGE statements.

If you customize your SQLJ application, you can assign one of the following values to an indicator variable in an SQLJ application to specify the type of the corresponding input host variable.

Indicator value	Equivalent constant	Meaning of value
-1	sqlj.runtime.ExecutionContext.DBNull	Null
-2, -3, -4, -6		Null
-5	sqlj.runtime.ExecutionContext.DBDefault	Default
-7	sqlj.runtime.ExecutionContext.DBUnassigned	Unassigned
short-value >=0	sqlj.runtime.ExecutionContext.DBNonNull	Non-null

If you do not customize the application, you can assign one of the following values to an indicator variable to specify the type of the corresponding input host variable.

Indicator value	Equivalent constant	Meaning of value
-1	sqlj.runtime.ExecutionContext.DBNull	Null
-7 <= *short-value* < -1		Null
0	sqlj.runtime.ExecutionContext.DBNonNull	Non-null

Indicator value	Equivalent constant	Meaning of value
short-value >0		Non-null

For output, SQLJ supports the use of indicator variables for the following statements:

- CALL with OUT or INOUT parameters
- FETCH *iterator* INTO *host-variable*
- SELECT ... INTO *host-variable-1*,...*host-variable-n*

SQLJ assigns one of the following values to an indicator variable to indicate whether an SQL NULL value was retrieved into the corresponding host variable.

Indicator value	Equivalent constant	Meaning of value
-1	sqlj.runtime.ExecutionContext.DBNull	Retrieved value is SQL NULL
0		Retrieved value is not SQL NULL

You cannot use indicator variables to update result sets. To assign null values or default values to result sets, or to indicate that columns are unassigned, call `ResultSet.updateObject` on the underlying JDBC ResultSet objects of the SQLJ iterators.

The following examples demonstrate how to use indicator variables.

All examples require that the data server supports extended indicators.

Example of using indicators to assign the default value to columns during an INSERT:

In this example, the MGRNO and LOCATION columns need to be set to their default values. To do this, the code performs these steps:

1. Assigns the value `ExecutionContext.DBNonNull` to the indicator variables (deptInd, dNameInd, rptDeptInd) for the input host variables (dept, dName, rptDept) that send non-default values to the target columns.
2. Assigns the value `ExecutionContext.DBDefault` to the indicator variables (mgrInd, locnInd) for the input host variables (mgr, locn) that send default values to the target columns.
3. Executes an INSERT statement with the host variable and indicator variable pairs as input.

The numbers to the right of selected statements correspond to the previously described steps.

```
import sqlj.runtime.*;
…
String dept = "F01";
String dName = "SHIPPING";
String rptDept = "A00";
String mgr, locn = null;
short deptInd, dNameInd, mgrInd, rptDeptInd, locnInd;
// Set indicator variables for dept, dName, rptDept to non-null
deptInd = dNameInd = rptDeptInd = ExecutionContext.DBNonNull;   1
mgrInd = ExecutionContext.DBDefault;                            2
locnInd = ExecutionContext.DBDefault;
#sql [ctxt]                                                     3
  {INSERT INTO DEPARTMENT
    (DEPTNO, DEPTNAME, MGRNO, ADMRDEPT, LOCATION)
    VALUES (:dept :deptInd, :dName :dNameInd,:mgr :mgrInd,
    :rptDept :rptDeptInd, :locn :locnInd)};
```

Example of using indicators to assign the default value to leave column values unassigned during an UPDATE:

In this example, in rows for department F01, the MGRNO column needs to be set to its default value, the DEPTNAME column value needs to be changed to RECEIVING, and the DEPTNO, DEPTNAME, ADMRDEPT, and LOCATION columns need to remain unchanged. To do this, the code performs these steps:

1. Assigns the new value for the DEPTNAME column to the dName input host variable.

2. Assigns the value `ExecutionContext.DBDefault` to the indicator variable (mgrInd) for the input host variable (mgr) that sends the default value to the target column.
3. Assigns the value `ExecutionContext.DBUnassigned` to the indicator variables (deptInd, dNameInd, rptDeptInd, and locnInd) for the input host variables (dept, dName, rptDept, and locn) that need to remain unchanged by the UPDATE operation.
4. Executes an UPDATE statement with the host variable and indicator variable pairs as input.

The numbers to the right of selected statements correspond to the previously described steps.

```
import sqlj.runtime.*;
…
String dept = null;
String dName = "RECEIVING";                                          1
String rptDept = null;
String mgr, locn = null;
short deptInd, dNameInd, mgrInd, rptDeptInd, locnInd;
dNameInd = ExecutionContext.DBNonNull;
mgrInd = ExecutionContext.DBDefault;                                 2
deptInd = rptDeptInd = locnInd = ExecutionContext.DBUnassigned;      3
#sql [ctxt]                                                          4
  {UPDATE DEPARTMENT
    SET DEPTNO = :dept :deptInd,
        DEPTNAME = :dName :dNameInd,
        MGRNO = :mgr :mgrInd,
        ADMRDEPT = :rptDept :rptDeptInd,
        LOCATION = :locn :locnInd
    WHERE DEPTNO = "F01"
  };
```

Example of using indicators to retrieve NULL values from columns:

In this example, the HIREDATE column can return the NULL value. To handle this case, the code performs these steps:

1. Defines an indicator variable to indicate when the NULL value is returned from HIREDATE.
2. Executes FETCH statements with the host variable and indicator variable pairs as output.
3. Checks the indicator variable to determine whether a NULL value was returned.

The numbers to the right of selected statements correspond to the previously described steps.

```
import sqlj.runtime.*;
…
#sql iterator ByPos(String, Date);  // Declare positioned iterator ByPos
{
  …
  ByPos positer;                    // Declare object of ByPos class
  String name = null;               // Declare host variables
  Date hrdate = null;
  short indhrdate = null;           // Declare indicator variable      1
  #sql [ctxt] positer =
    {SELECT LASTNAME, HIREDATE FROM EMPLOYEE};
                                    // Assign the result table of the SELECT
                                    // to iterator object positer
  #sql {FETCH :positer INTO :name, :hrdate :indhrdate };              2
                                    // Retrieve the first row
  while (!positer.endFetch())       // Check whether the FETCH returned a row
  { if(indhrdate == ExecutionContext.DBNonNull {                      3
     System.out.println(name + " was hired in " +
      hrdate); }
    else {
     System.out.println(name + " has no hire date "); }
    #sql {FETCH :positer INTO :name, :hrdate };
                                    // Fetch the next row
  }
  positer.close();                  // Close the iterator             5
}
```

Example of assigning default values to result set columns:

In this example, the HIREDATE column in a result set needs to be set to its default value. To do this, the code performs these steps:

1. Retrieves the underlying `ResultSet` from the iterator that holds the retrieved data.
2. Executes the `ResultSet.updateObject` method with the `DB2PreparedStatement.DB_PARAMETER_DEFAULT` constant to assign the default value to the result set column.

The numbers to the right of selected statements correspond to the previously described steps.

```
#sql public iterator sensitiveUpdateIter
 implements sqlj.runtime.Scrollable, sqlj.runtime.ForUpdate
 with (sensitivity=sqlj.runtime.ResultSetIterator.SENSITIVE,
 updateColumns="LASTNAME, HIREDATE") (String, Date);

  String name;                    // Declare host variables
  Date hrdate;

sensitiveUpdateIter iter = null;
#sql [ctx] iter = { SELECT LASTNAME, HIREDATE FROM EMPLOYEE};

iter.next();

java.sql.ResultSet rs =  iter.getResultSet();                     1
rs.updateString("LASTNAME", "FORREST");
rs.updateObject
 (2, com.ibm.db2.jcc.DB2PreparedStatement.DB_PARAMETER_DEFAULT);); 2,3
rs.updateRow();
iter.close();
```

Comments in an SQLJ application

To document your SQLJ program, you need to include comments. You can use Java comments outside of SQLJ statements and SQL or Java comments in SQLJ statements.

You can include Java comments outside SQLJ clauses, wherever the Java language permits them. Within an SQLJ clause, you can use comments in the following places:

- Within a host expression (enclosed in /* and */ or preceded by //).
- Within an SQL statement in an executable clause, if the data server supports a comment within the SQL statement.
  - For connections to Db2 data servers or Informix data servers, comments can be:
    - Anywhere in the SQL statement text, and enclosed in /* and */ pairs. /* and */ pairs can be nested.
    - At the end of the SQL statement text, and preceded by two hyphens (--).
  - For connections to Informix data servers only, comments can be enclosed in left curly bracket ({) and right curly bracket (}) pairs.

SQL statement execution in SQLJ applications

You execute SQL statements in a traditional SQL program to create tables, update data in tables, retrieve data from the tables, call stored procedures, or commit or roll back transactions. In an SQLJ program, you also execute these statements, within SQLJ *executable clauses*.

An executable clause can have one of the following general forms:

```
#sql [connection-context] {sql-statement};
#sql [connection-context,execution-context] {sql-statement};
#sql [execution-context] {sql-statement};
```

execution-context specification
In an executable clause, you should **always** specify an explicit connection context, with one exception: you do not specify an explicit connection context for a FETCH statement. You include an execution context only for specific cases. See "Control the execution of SQL statements in SQLJ" for information about when you need an execution context.

connection-context specification
In an executable clause, if you do not explicitly specify a connection context, the executable clause uses the default connection context.

Creating and modifying database objects in an SQLJ application

Use SQLJ executable clauses to execute data definition statements (CREATE, ALTER, DROP, GRANT, REVOKE) or to execute INSERT, searched or positioned UPDATE, and searched or positioned DELETE statements.

Example

The following executable statements demonstrate an INSERT, a searched UPDATE, and a searched DELETE:

```
#sql [myConnCtx] {INSERT INTO DEPARTMENT VALUES
  ("X00","Operations 2","000030","E01",NULL)};
#sql [myConnCtx] {UPDATE DEPARTMENT
  SET MGRNO="000090" WHERE MGRNO="000030"};
#sql [myConnCtx] {DELETE FROM DEPARTMENT
  WHERE DEPTNO="X00"};
```

Performing positioned UPDATE and DELETE operations in an SQLJ application

As in database applications in other languages, performing positioned UPDATEs and DELETEs with SQLJ is an extension of retrieving rows from a result table.

Procedure

The basic steps are:

1. Declare the iterator.

   The iterator can be positioned or named. For positioned UPDATE or DELETE operations, declare the iterator as updatable, using one or both of the following clauses:

   implements sqlj.runtime.ForUpdate
   This clause causes the generated iterator class to include methods for using updatable iterators. This clause is required for programs with positioned UPDATE or DELETE operations.

   with (updateColumns="*column-list*")
   This clause specifies a comma-separated list of the columns of the result table that the iterator will update. This clause is optional.

   You need to declare the iterator as `public`, so you need to follow the rules for declaring and using `public` iterators in the same file or different files.

   If you declare the iterator in a file by itself, any SQLJ source file that has addressability to the iterator and imports the generated class can retrieve data and execute positioned UPDATE or DELETE statements using the iterator.

   The authorization ID under which a positioned UPDATE or DELETE statement executes depends on whether the statement executes statically or dynamically. If the statement executes statically, the authorization ID is the owner of the plan or package that includes the statement. If the statement executes dynamically the authorization ID is determined by the DYNAMICRULES behavior that is in effect. For the IBM Data Server Driver for JDBC and SQLJ, the behavior is always DYNAMICRULES BIND.
2. Disable autocommit mode for the connection.

   If autocommit mode is enabled, a COMMIT operation occurs every time the positioned UPDATE statement executes, which causes the iterator to be destroyed unless the iterator has the `with (holdability=true)` attribute. Therefore, you need to turn autocommit off to prevent COMMIT

operations until you have finished using the iterator. If you want a COMMIT to occur after every update operation, an alternative way to keep the iterator from being destroyed after each COMMIT operation is to declare the iterator `with (holdability=true)`.

3. Create an instance of the iterator class.

   This is the same step as for a non-updatable iterator.

4. Assign the result table of a SELECT to an instance of the iterator.

   This is the same step as for a non-updatable iterator. The SELECT statement must not include a FOR UPDATE clause.

5. Retrieve and update rows.

   For a positioned iterator, do this by performing the following actions in a loop:

   a) Execute a FETCH statement in an executable clause to obtain the current row.

   b) Test whether the iterator is pointing to a row of the result table by invoking the `PositionedIterator.endFetch` method.

   c) If the iterator is pointing to a row of the result table, execute an SQL UPDATE... WHERE CURRENT OF *:iterator-object* statement in an executable clause to update the columns in the current row. Execute an SQL DELETE... WHERE CURRENT OF *:iterator-object* statement in an executable clause to delete the current row.

   For a named iterator, do this by performing the following actions in a loop:

   a) Invoke the `next` method to move the iterator forward.

   b) Test whether the iterator is pointing to a row of the result table by checking whether `next` returns `true`.

   c) Execute an SQL UPDATE... WHERE CURRENT OF *iterator-object* statement in an executable clause to update the columns in the current row. Execute an SQL DELETE... WHERE CURRENT OF *iterator-object* statement in an executable clause to delete the current row.

6. Close the iterator.

   Use the `close` method to do this.

Example

The following code shows how to declare a positioned iterator and use it for positioned UPDATEs. The numbers to the right of selected statements correspond to the previously described steps.

First, in one file, declare positioned iterator UpdByPos, specifying that you want to use the iterator to update column SALARY:

```
import java.math.*;    // Import this class for BigDecimal data type
#sql public iterator UpdByPos implements sqlj.runtime.ForUpdate       1
  with(updateColumns="SALARY") (String, BigDecimal);
```

Figure 27. Example of declaring a positioned iterator for a positioned UPDATE

Then, in another file, use UpdByPos for a positioned UPDATE, as shown in the following code fragment:

```
import sqlj.runtime.*;       // Import files for SQLJ and JDBC APIs
import java.sql.*;
import java.math.*;          // Import this class for BigDecimal data type
import UpdByPos;             // Import the generated iterator class that
                             // was created by the iterator declaration clause
                             // for UpdByName in another file
#sql context HSCtx;          // Create a connection context class HSCtx
public static void main (String args[])
{
  try {
    Class.forName("com.ibm.db2.jcc.DB2Driver");
  }
  catch (ClassNotFoundException e) {
    e.printStackTrace();
          }
  Connection HSjdbccon=
  DriverManager.getConnection("jdbc:db2:SANJOSE");
                     // Create a JDBC connection object
  HSjdbccon.setAutoCommit(false);
                     // Set autocommit off so automatic commits      2
                     // do not destroy the cursor between updates
  HSCtx myConnCtx=new HSCtx(HSjdbccon);
                     // Create a connection context object
  UpdByPos upditer;  // Declare iterator object of UpdByPos class    3
  String empnum;     // Declares host variable to receive EMPNO
  BigDecimal sal;    // and SALARY column values
  #sql [myConnCtx]
    upditer = {SELECT EMPNO, SALARY FROM EMPLOYEE                    4
      WHERE WORKDEPT='D11'};
                     // Assign result table to iterator object
  #sql {FETCH :upditer INTO :empnum,:sal};                           5a
                     // Move cursor to next row
  while (!upditer.endFetch())                                        5b
                     // Check if on a row
  {
    #sql [myConnCtx] {UPDATE EMPLOYEE SET SALARY=SALARY*1.05
      WHERE CURRENT OF :upditer};                                    5c
                     // Perform positioned update
    System.out.println("Updating row for " + empnum);
    #sql {FETCH :upditer INTO :empnum,:sal};
                     // Move cursor to next row
  }
  upditer.close();   // Close the iterator                          6
  #sql [myConnCtx] {COMMIT};
                     // Commit the changes
  myConnCtx.close(); // Close the connection context
}
```

Figure 28. Example of performing a positioned UPDATE with a positioned iterator

The following code shows how to declare a named iterator and use it for positioned UPDATEs. The numbers to the right of selected statements correspond to the previously described steps.

First, in one file, declare named iterator UpdByName, specifying that you want to use the iterator to update column SALARY:

```
import java.math.*;          // Import this class for BigDecimal data type
#sql public iterator UpdByName implements sqlj.runtime.ForUpdate    1
  with(updateColumns="SALARY") (String EmpNo, BigDecimal Salary);
```

Figure 29. Example of declaring a named iterator for a positioned UPDATE

Then, in another file, use UpdByName for a positioned UPDATE, as shown in the following code fragment:

```
import sqlj.runtime.*;       // Import files for SQLJ and JDBC APIs
import java.sql.*;
import java.math.*;          // Import this class for BigDecimal data type
import UpdByName;            // Import the generated iterator class that
                             // was created by the iterator declaration clause
                             // for UpdByName in another file
#sql context HSCtx;          // Create a connection context class HSCtx
public static void main (String args[])
{
  try {
    Class.forName("com.ibm.db2.jcc.DB2Driver");
  }
  catch (ClassNotFoundException e) {
    e.printStackTrace();
          }
  Connection HSjdbccon=
  DriverManager.getConnection("jdbc:db2:SANJOSE");
                             // Create a JDBC connection object
  HSjdbccon.setAutoCommit(false);
                             // Set autocommit off so automatic commits  2
                             // do not destroy the cursor between updates
  HSCtx myConnCtx=new HSCtx(HSjdbccon);
                             // Create a connection context object
  UpdByName upditer;                                                    3
                             // Declare iterator object of UpdByName class
  String empnum;               // Declare host variable to receive EmpNo
                             // column values
  #sql [myConnCtx]
    upditer = {SELECT EMPNO, SALARY FROM EMPLOYEE                       4
      WHERE WORKDEPT='D11'};
                             // Assign result table to iterator object
  while (upditer.next())                                                5a,5b
                             // Move cursor to next row and
                             // check ifon a row
  {
    empnum = upditer.EmpNo();  // Get employee number from current row
    #sql [myConnCtx]
      {UPDATE EMPLOYEE SET SALARY=SALARY*1.05
        WHERE CURRENT OF :upditer};                                     5c
                             // Perform positioned update
    System.out.println("Updating row for " + empnum);
  }
  upditer.close();           // Close the iterator                     6
  #sql [myConnCtx] {COMMIT};
                             // Commit the changes
  myConnCtx.close();         // Close the connection context
}
```

Figure 30. Example of performing a positioned UPDATE with a named iterator

Related concepts

“Iterators as passed variables for positioned UPDATE or DELETE operations in an SQLJ application” on page 137
SQLJ allows iterators to be passed between methods as variables.

“Data retrieval in SQLJ applications” on page 142
SQLJ applications use a *result set iterator* to retrieve result sets. Like a cursor, a result set iterator can be non-scrollable or scrollable.

Authorization IDs and dynamic SQL (Db2 SQL)

Related tasks

“Creating and modifying database objects in an SQLJ application” on page 133
Use SQLJ executable clauses to execute data definition statements (CREATE, ALTER, DROP, GRANT, REVOKE) or to execute INSERT, searched or positioned UPDATE, and searched or positioned DELETE statements.

“Connecting to a data source using SQLJ” on page 121

In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

Iterators as passed variables for positioned UPDATE or DELETE operations in an SQLJ application

SQLJ allows iterators to be passed between methods as variables.

An iterator that is used for a positioned UPDATE or DELETE statement can be identified only at runtime. The same SQLJ positioned UPDATE or DELETE statement can be used with different iterators at runtime. If you specify a value of YES for -staticpositioned when you customize your SQLJ application as part of the program preparation process, the SQLJ customizer prepares positioned UPDATE or DELETE statements to execute statically. In this case, the customizer must determine which iterators belong with which positioned UPDATE or DELETE statements. The SQLJ customizer does this by matching iterator data types to data types in the UPDATE or DELETE statements. However, if there is not a unique mapping of tables in UPDATE or DELETE statements to iterator classes, the SQLJ customizer cannot determine exactly which iterators and UPDATE or DELETE statements go together. The SQLJ customizer must arbitrarily pair iterators with UPDATE or DELETE statements, which can sometimes result in SQL errors. The following code fragments illustrate this point.

```
#sql iterator GeneralIter implements sqlj.runtime.ForUpdate
  ( String );

  public static void main ( String args[] )
  {
…
    GeneralIter iter1 = null;
    #sql [ctxt] iter1 = { SELECT CHAR_COL1 FROM TABLE1 };

    GeneralIter iter2 = null;
    #sql [ctxt] iter2 = { SELECT CHAR_COL2 FROM TABLE2 };
…

    doUpdate ( iter1 );
  }

  public static void doUpdate ( GeneralIter iter )
  {
    #sql [ctxt] { UPDATE TABLE1 ... WHERE CURRENT OF :iter };
  }
```

Figure 31. Static positioned UPDATE that fails

In this example, only one iterator is declared. Two instances of that iterator are declared, and each is associated with a different SELECT statement that retrieves data from a different table. During customization and binding with -staticpositioned YES, SQLJ creates two DECLARE CURSOR statements, one for each SELECT statement, and attempts to bind an UPDATE statement for each cursor. However, the bind process fails with SQLCODE -509 when `UPDATE TABLE1 ... WHERE CURRENT OF :iter` is bound for the cursor for `SELECT CHAR_COL2 FROM TABLE2` because the table for the UPDATE does not match the table for the cursor.

You can avoid a bind time error for a program like the one in Figure 31 on page 137 by specifying the bind option SQLERROR(CONTINUE). However, this technique has the drawback that it causes the database manager to build a package, regardless of the SQL errors that are in the program. A better technique is to write the program so that there is a one-to-one mapping between tables in positioned UPDATE or DELETE statements and iterator classes. Figure 32 on page 138 shows an example of how to do this.

```
#sql iterator Table2Iter(String);
#sql iterator Table1Iter(String);
  public static void main ( String args[] )
  {
…
    Table2Iter iter2 = null;
    #sql [ctxt] iter2 = { SELECT CHAR_COL2 FROM TABLE2 };

    Table1Iter iter1 = null;
    #sql [ctxt] iter1 = { SELECT CHAR_COL1 FROM TABLE1 };
…

    doUpdate(iter1);

  }

 public static void doUpdate ( Table1Iter iter )
  {
    …
    #sql [ctxt] { UPDATE TABLE1 ... WHERE CURRENT OF :iter };
    …
  }
 public static void doUpdate ( Table2Iter iter )
  {
    …
    #sql [ctxt] { UPDATE TABLE2 ... WHERE CURRENT OF :iter };
    …
  }
```

Figure 32. Static positioned UPDATE that succeeds

With this method of coding, each iterator class is associated with only one table. Therefore, the data server bind process can always associate the positioned UPDATE statement with a valid iterator.

Making batch updates in SQLJ applications

The IBM Data Server Driver for JDBC and SQLJ supports batch updates in SQLJ. With batch updates, instead of updating rows of a table one at a time, you can direct SQLJ to execute a group of updates at the same time.

About this task

You can include the following types of statements in a batch update:

- Searched INSERT, UPDATE, or DELETE, or MERGE statements
- CREATE, ALTER, DROP, GRANT, or REVOKE statements
- CALL statements with input parameters only

Unlike JDBC, SQLJ allows heterogeneous batches that contain statements with input parameters or host expressions. You can therefore combine any of the following items in an SQLJ batch:

- Instances of the same statement
- Different statements
- Statements with different numbers of input parameters or host expressions
- Statements with different data types for input parameters or host expressions
- Statements with no input parameters or host expressions

For all cases except batch inserts, when an error occurs during execution of a statement in a batch, the remaining statements are executed, and a `BatchUpdateException` is thrown after all the statements in the batch have executed.

For batch inserts, the behavior is as follows:

- If you set atomicMultiRowInsert to `DB2BaseDataSource.YES` (1) when you run db2sqljcustomize, and the target data server is Db2 for z/OS, when an error occurs during execution of an INSERT statement in a batch, the remaining statements are not executed, and a `BatchUpdateException` is thrown.

- If you do not set atomicMultiRowInsert to DB2BaseDataSource.YES (1) when you run db2sqljcustomize, or the target data server is not Db2 for z/OS, when an error occurs during execution of an INSERT statement in a batch, the remaining statements are executed, and a BatchUpdateException is thrown after all the statements in the batch have executed.

To obtain information about warnings, use the ExecutionContext.getWarnings method on the ExecutionContext that you used to submit statements to be batched. You can then retrieve an error description, SQLSTATE, and error code for each SQLWarning object.

When a batch is executed implicitly because the program contains a statement that cannot be added to the batch, the batch is executed before the new statement is processed. If an error occurs during execution of the batch, the statement that caused the batch to execute does not execute.

Procedure

The basic steps for creating, executing, and deleting a batch of statements are:

1. Disable AutoCommit for the connection.

   Do this so that you can control whether to commit changes to already-executed statements when an error occurs during batch execution.
2. Acquire an execution context.

   All statements that execute in a batch must use this execution context.
3. Invoke the ExecutionContext.setBatching(true) method to create a batch.

   Subsequent batchable statements that are associated with the execution context that you created in step "2" on page 139 are added to the batch for later execution.

   If you want to batch sets of statements that are not batch compatible in parallel, you need to create an execution context for each set of batch compatible statements.
4. Include SQLJ executable clauses for SQL statements that you want to batch.

   These clauses must include the execution context that you created in step "2" on page 139.

   If an SQLJ executable clause has input parameters or host expressions, you can include the statement in the batch multiple times with different values for the input parameters or host expressions.

   To determine whether a statement was added to an existing batch, was the first statement in a new batch, or was executed inside or outside a batch, invoke the ExecutionContext.getUpdateCount method. This method returns one of the following values:

   ExecutionContext.ADD_BATCH_COUNT
   This is a constant that is returned if the statement was added to an existing batch.

   ExecutionContext.NEW_BATCH_COUNT
   This is a constant that is returned if the statement was the first statement in a new batch.

   ExecutionContext.EXEC_BATCH_COUNT
   This is a constant that is returned if the statement was part of a batch, and the batch was executed.

   Other integer
   This value is the number of rows that were updated by the statement. This value is returned if the statement was executed rather than added to a batch.
5. Execute the batch explicitly or implicitly.

   - Invoke the ExecutionContext.executeBatch method to execute the batch explicitly.

     executeBatch returns an integer array that contains the number of rows that were updated by each statement in the batch. The order of the elements in the array corresponds to the order in which you first added statements to the batch. For each statement in the batch that is run several times with different sets of input parameter or host expression values, the order of the array elements for that statement is the order in which you added the values to the statement.
   - Alternatively, a batch executes implicitly under the following circumstances:

- You include a batchable statement in your program that is not compatible with statements that are already in the batch. In this case, SQLJ executes the statements that are already in the batch and creates a new batch that includes the incompatible statement.
- You include a statement in your program that is not batchable. In this case, SQLJ executes the statements that are already in the batch. SQLJ also executes the statement that is not batchable.
- After you invoke the `ExecutionContext.setBatchLimit(n)` method, you add a statement to the batch that brings the number of statements in the batch to *n* or greater. *n* can have one of the following values:

  `ExecutionContext.UNLIMITED_BATCH`
  This constant indicates that implicit execution occurs only when SQLJ encounters a statement that is batchable but incompatible, or not batchable. Setting this value is the same as not invoking `setBatchLimit`.

  `ExecutionContext.AUTO_BATCH`
  This constant indicates that implicit execution occurs when the number of statements in the batch reaches a number that is set by SQLJ.

  Positive integer
  When this number of statements have been added to the batch, SQLJ executes the batch implicitly. However, the batch might be executed before this many statements have been added if SQLJ encounters a statement that is batchable but incompatible, or not batchable.

  To determine the number of rows that were updated by a batch that was executed implicitly, invoke the `ExecutionContext.getBatchUpdateCounts` method. `getBatchUpdateCounts` returns an integer array that contains the number of rows that were updated by each statement in the batch. The order of the elements in the array corresponds to the order in which you added statements to the batch. Each array element can be one of the following values:

  -2
  This value indicates that the SQL statement executed successfully, but the number of rows that were updated could not be determined.

  -3
  This value indicates that the SQL statement failed.

  Other integer
  This value is the number of rows that were updated by the statement.

6. Optionally, when all statements have been added to the batch, disable batching.

   Do this by invoking the `ExecutionContext.setBatching(false)` method. When you disable batching, you can still execute the batch implicitly or explicitly, but no more statements are added to the batch. Disabling batching is useful when a batch already exists, and you want to execute a batch compatible statement, rather than adding it to the batch.

   If you want to clear a batch without executing it, invoke the `ExecutionContext.cancel` method.
7. If batch execution was implicit, perform a final, explicit `executeBatch` to ensure that all statements have been executed.

Example

The following example demonstrates batching of UPDATE statements. The numbers to the right of selected statements correspond to the previously described steps.

```
#sql iterator GetMgr(String);       // Declare positioned iterator
…
{
  GetMgr deptiter;                  // Declare object of GetMgr class
  String mgrnum = null;             // Declare host variable for manager number
  int raise = 400;                  // Declare raise amount
  int currentSalary;                // Declare current salary
  String url, username, password;   // Declare url, user ID, password
  …
  TestContext c1 = new TestContext (url, username, password, false); 1
  ExecutionContext ec = new ExecutionContext();                      2
  ec.setBatching(true);                                              3
```

```
  #sql [c1] deptiter =
    {SELECT MGRNO FROM DEPARTMENT};
                                    // Assign the result table of the SELECT
                                    // to iterator object deptiter
  #sql {FETCH :deptiter INTO :mgrnum};
                                    // Retrieve the first manager number
  while (!deptiter.endFetch()) {    // Check whether the FETCH returned a row
    #sql [c1]
      {SELECT SALARY INTO :currentSalary FROM EMPLOYEE
        WHERE EMPNO=:mgrnum};
    #sql [c1, ec]                                                    4
      {UPDATE EMPLOYEE SET SALARY=:(currentSalary+raise)
        WHERE EMPNO=:mgrnum};
    #sql {FETCH :deptiter INTO :mgrnum };
                                    // Fetch the next row
  }
  ec.executeBatch();                                                 5
  ec.setBatching(false);                                             6
  #sql [c1] {COMMIT};
  deptiter.close();                 // Close the iterator
  c1.close();                       // Close the connection
}
```

The following example demonstrates batching of INSERT statements. Suppose that ATOMICTBL is defined like this:

```
CREATE TABLE ATOMICTBL(
 INTCOL INTEGER NOT NULL UNIQUE,
 CHARCOL VARCHAR(10))
```

Also suppose that the table already has a row with the values 2 and "val2". Because of the uniqueness constraint on INTCOL, when the following code is executed, the second INSERT statement in the batch fails.

If the target data server is Db2 for z/OS, and this application is customized without atomicMultiRowInsert set to DB2BaseDataSource.YES, the batch INSERT is non-atomic, so the first set of values is inserted in the table. However, if the application is customized with atomicMultiRowInsert set to DB2BaseDataSource.YES, the batch INSERT is atomic, so the first set of values is not inserted.

The numbers to the right of selected statements correspond to the previously described steps.

```
 …
TestContext ctx = new TestContext (url, username, password, false);  1
ctx.getExecutionContext().setBatching(true);                         2,3
try {
  for (int i = 1; i<= 2; ++i) {
   if (i == 1) {
    intVar = 3;
    strVar = "val1";
   {
   if (i == 2) {
    intVar = 1;
    strVar = "val2";
   }
   #sql [ctx] {INSERT INTO ATOMICTBL values(:intVar, :strVar)};      4
  }
  int[] counts = ctx.getExecutionContext().executeBatch();           5
  for (int i = 0; i<counts.length; ++i) {
    System.out.println(" count[" + i + "]:" + counts[i]);
  }
}
catch (SQLException e) {
  System.out.println(" Exception Caught: " + e.getMessage());
   SQLException excp = null;
  if (e instanceof SQLException)
  {
    System.out.println(" SQLCode: " + ((SQLException)e).getErrorCode() + "
      Message: " + e.getMessage() );
    excp = ((SQLException)e).getNextException();
    while (  excp != null ) {
      System.out.println(" SQLCode: " + ((SQLException)excp).getErrorCode() +
        " Message: " + excp.getMessage() );
      excp = excp.getNextException();
    }
```

```
  }
}
```

Related tasks

“Controlling the execution of SQL statements in SQLJ” on page 158
You can use selected methods of the SQLJ `ExecutionContext` class to control or monitor the execution of SQL statements.

“Connecting to a data source using SQLJ” on page 121
In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

Related reference

“sqlj.runtime.SQLNullException class” on page 385
The `sqlj.runtime.SQLNullException` class is derived from the `java.sql.SQLException` class.

“db2sqljcustomize - SQLJ profile customizer” on page 516
db2sqljcustomize processes an SQLJ profile, which contains embedded SQL statements.

Data retrieval in SQLJ applications

SQLJ applications use a *result set iterator* to retrieve result sets. Like a cursor, a result set iterator can be non-scrollable or scrollable.

Just as in database applications in other languages, if you want to retrieve a single row from a table in an SQLJ application, you can write a SELECT INTO statement with a WHERE clause that defines a result table that contains only that row:

```
#sql [myConnCtx] {SELECT DEPTNO INTO :hvdeptno
  FROM DEPARTMENT WHERE DEPTNAME="OPERATIONS"};
```

However, most SELECT statements that you use create result tables that contain many rows. In database applications in other languages, you use a cursor to select the individual rows from the result table. That cursor can be non-scrollable, which means that when you use it to fetch rows, you move the cursor serially, from the beginning of the result table to the end. Alternatively, the cursor can be scrollable, which means that when you use it to fetch rows, you can move the cursor forward, backward, or to any row in the result table.

This topic discusses how to use non-scrollable iterators. For information on using scrollable iterators, see "Use scrollable iterators in an SQLJ application".

A result set iterator is a Java object that you use to retrieve rows from a result table. Unlike a cursor, a result set iterator can be passed as a parameter to a method.

The basic steps in using a result set iterator are:

1. Declare the iterator, which results in an iterator class
2. Define an instance of the iterator class.
3. Assign the result table of a SELECT to an instance of the iterator.
4. Retrieve rows.
5. Close the iterator.

There are two types of iterators: *positioned iterators* and *named iterators*. Positioned iterators extend the interface `sqlj.runtime.PositionedIterator`. Positioned iterators identify the columns of a result table by their position in the result table. Named iterators extend the interface `sqlj.runtime.NamedIterator`. Named iterators identify the columns of the result table by result table column names.

Using a named iterator in an SQLJ application

Use a named iterator to refer to each of the columns in a result table by name.

Procedure

The steps in using a named iterator are:

1. Declare the iterator.

   You declare any result set iterator using an *iterator declaration clause*. This causes an iterator class to be created that has the same name as the iterator. For a named iterator, the iterator declaration clause specifies the following information:

   - The name of the iterator
   - A list of column names and Java data types
   - Information for a Java class declaration, such as whether the iterator is `public` or `static`
   - A set of attributes, such as whether the iterator is holdable, or whether its columns can be updated

   When you declare a named iterator for a query, you specify names for each of the iterator columns. Those names must match the names of columns in the result table for the query. An iterator column name and a result table column name that differ only in case are considered to be matching names. The named iterator class that results from the iterator declaration clause contains *accessor methods*. There is one accessor method for each column of the iterator. Each accessor method name is the same as the corresponding iterator column name. You use the accessor methods to retrieve data from columns of the result table.

   You need to specify Java data types in the iterators that closely match the corresponding column data types. See "Java, JDBC, and SQL data types" for a list of the best mappings between Java data types and table column data types.

   You can declare an iterator in a number of ways. However, because a Java class underlies each iterator, you need to ensure that when you declare an iterator, the underlying class obeys Java rules. For example, iterators that contain a *with-clause* must be declared as `public`. Therefore, if an iterator needs to be `public`, it can be declared only where a `public` class is allowed. The following list describes some alternative methods of declaring an iterator:

   - As `public`, in a source file by itself

     This method lets you use the iterator declaration in other code modules, and provides an iterator that works for all SQLJ applications. In addition, there are no concerns about having other top-level classes or `public` classes in the same source file.
   - As a top-level class in a source file that contains other top-level class definitions

     Java allows only one public, top-level class in a code module. Therefore, if you need to declare the iterator as public, such as when the iterator includes a with-clause, no other classes in the code module can be declared as public.
   - As a nested static class within another class

     Using this alternative lets you combine the iterator declaration with other class declarations in the same source file, declare the iterator and other classes as public, and make the iterator class visible to other code modules or packages. However, when you reference the iterator from outside the nesting class, you must fully-qualify the iterator name with the name of the nesting class.
   - As an inner class within another class

     When you declare an iterator in this way, you can instantiate it only within an instance of the nesting class. However, you can declare the iterator and other classes in the file as public.

     You cannot cast a JDBC `ResultSet` to an iterator if the iterator is declared as an inner class. This restriction does not apply to an iterator that is declared as a static nested class. See "Use SQLJ and JDBC in the same application" for more information on casting a `ResultSet` to a iterator.
2. Create an instance of the iterator class.

You declare an object of the named iterator class to retrieve rows from a result table.

3. Assign the result table of a SELECT to an instance of the iterator.

   To assign the result table of a SELECT to an iterator, you use an SQLJ *assignment clause*. The format of the assignment clause for a named iterator is:

   ```
   #sql context-clause iterator-object={select-statement};
   ```

   See "SQLJ assignment-clause" and "SQLJ context-clause" for more information.

4. Retrieve rows.

   Do this by invoking accessor methods in a loop. Accessor methods have the same names as the corresponding columns in the iterator, and have no parameters. An accessor method returns the value from the corresponding column of the current row in the result table. Use the `NamedIterator.next()` method to move the cursor forward through the result table.

   To test whether you have retrieved all rows, check the value that is returned when you invoke the `next` method. `next` returns a `boolean` with a value of `false` if there is no next row.

5. Close the iterator.

   Use the `NamedIterator.close` method to do this.

Example

The following code demonstrates how to declare and use a named iterator. The numbers to the right of selected statements correspond to the previously-described steps.

```
#sql  iterator ByName(String LastName, Date HireDate);                  1
                                // Declare named iterator ByName
{
  …
  ByName nameiter;              // Declare object of ByName class        2
  #sql [ctxt]
 nameiter={SELECT LASTNAME, HIREDATE FROM EMPLOYEE};                     3
                                // Assign the result table of the SELECT
                                // to iterator object nameiter
  while (nameiter.next())       // Move the iterator through the result  4
                                // table and test whether all rows retrieved
  {
    System.out.println( nameiter.LastName() + " was hired on "
      + nameiter.HireDate());   // Use accessor methods LastName and
                                // HireDate to retrieve column values
  }
  nameiter.close();             // Close the iterator                    5
}
```

Figure 33. Example of using a named iterator

Related tasks

"Performing positioned UPDATE and DELETE operations in an SQLJ application" on page 133
As in database applications in other languages, performing positioned UPDATEs and DELETEs with SQLJ is an extension of retrieving rows from a result table.

"Using a positioned iterator in an SQLJ application" on page 144
Use a positioned iterator to refer to columns in a result table by their position in the result set.

Using a positioned iterator in an SQLJ application

Use a positioned iterator to refer to columns in a result table by their position in the result set.

Procedure

The steps in using a positioned iterator are:

1. Declare the iterator.

You declare any result set iterator using an *iterator declaration clause*. This causes an iterator class to be created that has the same name and attributes as the iterator. For a positioned iterator, the iterator declaration clause specifies the following information:

- The name of the iterator
- A list of Java data types
- Information for a Java class declaration, such as whether the iterator is `public` or `static`
- A set of attributes, such as whether the iterator is holdable, or whether its columns can be updated

The data type declarations represent columns in the result table and are referred to as columns of the result set iterator. The columns of the result set iterator correspond to the columns of the result table, in left-to-right order. For example, if an iterator declaration clause has two data type declarations, the first data type declaration corresponds to the first column in the result table, and the second data type declaration corresponds to the second column in the result table.

You need to specify Java data types in the iterators that closely match the corresponding column data types. See "Java, JDBC, and SQL data types" for a list of the best mappings between Java data types and column data types.

You can declare an iterator in a number of ways. However, because a Java class underlies each iterator, you need to ensure that when you declare an iterator, the underlying class obeys Java rules. For example, iterators that contain a *with-clause* must be declared as `public`. Therefore, if an iterator needs to be `public`, it can be declared only where a `public` class is allowed. The following list describes some alternative methods of declaring an iterator:

- As `public`, in a source file by itself

  This is the most versatile method of declaring an iterator. This method lets you use the iterator declaration in other code modules, and provides an iterator that works for all SQLJ applications. In addition, there are no concerns about having other top-level classes or `public` classes in the same source file.
- As a top-level class in a source file that contains other top-level class definitions

  Java allows only one public, top-level class in a code module. Therefore, if you need to declare the iterator as public, such as when the iterator includes a with-clause, no other classes in the code module can be declared as public.
- As a nested static class within another class

  Using this alternative lets you combine the iterator declaration with other class declarations in the same source file, declare the iterator and other classes as public, and make the iterator class visible from other code modules or packages. However, when you reference the iterator from outside the nesting class, you must fully-qualify the iterator name with the name of the nesting class.
- As an inner class within another class

  When you declare an iterator in this way, you can instantiate it only within an instance of the nesting class. However, you can declare the iterator and other classes in the file as public.

  You cannot cast a JDBC `ResultSet` to an iterator if the iterator is declared as an inner class. This restriction does not apply to an iterator that is declared as a static nested class. See "Use SQLJ and JDBC in the same application" for more information on casting a `ResultSet` to a iterator.

2. Create an instance of the iterator class.

   You declare an object of the positioned iterator class to retrieve rows from a result table.
3. Assign the result table of a SELECT to an instance of the iterator.

   To assign the result table of a SELECT to an iterator, you use an SQLJ *assignment clause*. The format of the assignment clause for a positioned iterator is:

   ```
   #sql context-clause iterator-object={select-statement};
   ```
4. Retrieve rows.

Do this by executing FETCH statements in executable clauses in a loop. The FETCH statements looks the same as a FETCH statements in other languages.

To test whether you have retrieved all rows, invoke the `PositionedIterator.endFetch` method after each FETCH. `endFetch` returns a `boolean` with the value `true` if the FETCH failed because there are no rows to retrieve.

5. Close the iterator.

   Use the `PositionedIterator.close` method to do this.

Example

The following code demonstrates how to declare and use a positioned iterator. The numbers to the right of selected statements correspond to the previously-described steps.

```
#sql iterator ByPos(String,Date); // Declare positioned iterator ByPos  1
{
  …
  ByPos positer;                  // Declare object of ByPos class    2
  String name = null;             // Declare host variables
  Date hrdate;
  #sql [ctxt] positer =
    {SELECT LASTNAME, HIREDATE FROM EMPLOYEE};                         3
                                  // Assign the result table of the SELECT
                                  // to iterator object positer
  #sql {FETCH :positer INTO :name, :hrdate };                          4
                                  // Retrieve the first row
  while (!positer.endFetch())     // Check whether the FETCH returned a row
  { System.out.println(name + " was hired in " +
      hrdate);
    #sql {FETCH :positer INTO :name, :hrdate };
                                  // Fetch the next row
  }
  positer.close();                // Close the iterator               5
}
```

Figure 34. Example of using a positioned iterator

Related concepts

“Data retrieval in SQLJ applications” on page 142
SQLJ applications use a *result set iterator* to retrieve result sets. Like a cursor, a result set iterator can be non-scrollable or scrollable.

Related tasks

“Performing positioned UPDATE and DELETE operations in an SQLJ application” on page 133
As in database applications in other languages, performing positioned UPDATEs and DELETEs with SQLJ is an extension of retrieving rows from a result table.

“Using a named iterator in an SQLJ application” on page 143
Use a named iterator to refer to each of the columns in a result table by name.

Multiple open iterators for the same SQL statement in an SQLJ application

With the IBM Data Server Driver for JDBC and SQLJ, your application can have multiple concurrently open iterators for a single SQL statement in an SQLJ application. With this capability, you can perform one operation on a table using one iterator while you perform a different operation on the same table using another iterator.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS, support for multiple open iterators on a single SQL statement must be enabled. To do that, set the db2.jcc.allowSqljDuplicateStaticQueries configuration property to YES or `true`.

When you use concurrently open iterators in an application, you should close iterators when you no longer need them to prevent excessive storage consumption in the Java heap.

The following examples demonstrate how to perform the same operations on a table without concurrently open iterators on a single SQL statement and with concurrently open iterators on a single SQL statement. These examples use the following iterator declaration:

```
import java.math.*;
#sql public iterator  MultiIter(String EmpNo, BigDecimal Salary);
```

Without the capability for multiple, concurrently open iterators for a single SQL statement, if you want to select employee and salary values for a specific employee number, you need to define a different SQL statement for each employee number, as shown in Figure 35 on page 147.

```
MultiIter iter1 = null;            // Iterator instance for retrieving
                                   // data for first employee
String EmpNo1 = "000100";          // Employee number for first employee
#sql [ctx] iter1 =
  {SELECT EMPNO, SALARY FROM EMPLOYEE WHERE EMPNO = :EmpNo1};
                                   // Assign result table to first iterator
MultiIter iter2 = null;            // Iterator instance for retrieving
                                   // data for second employee
String EmpNo2 = "000200";          // Employee number for second employee
#sql [ctx] iter2 =
  {SELECT EMPNO, SALARY FROM EMPLOYEE WHERE EMPNO = :EmpNo2};
                                   // Assign result table to second iterator
// Process with iter1
// Process with iter2
iter1.close();                     // Close the iterators
iter2.close();
```

Figure 35. Example of concurrent table operations using iterators with different SQL statements

Figure 36 on page 147 demonstrates how you can perform the same operations when you have the capability for multiple, concurrently open iterators for a single SQL statement.

```
…
MultiIter iter1 = openIter("000100"); // Invoke openIter to assign the result table
                                      // (for employee 100) to the first iterator
MultiIter iter2 = openIter("000200"); // Invoke openIter to assign the result
                                      // table to the second iterator
                                      // iter1 stays open when iter2 is opened
// Process with iter1
// Process with iter2
…
iter1.close();                        // Close the iterators
iter2.close();
…
public MultiIter openIter(String EmpNo)
                                      // Method to assign a result table
                                      // to an iterator instance
{
  MultiIter iter;
  #sql [ctxt] iter =
    {SELECT EMPNO, SALARY FROM EMPLOYEE WHERE EMPNO = :EmpNo};
  return iter;                        // Method returns an iterator instance
}
```

Figure 36. Example of concurrent table operations using iterators with the same SQL statement

Multiple open instances of an iterator in an SQLJ application

Multiple instances of an iterator can be open concurrently in a single SQLJ application. One application for this ability is to open several instances of an iterator that uses host expressions. Each instance can use a different set of host expression values.

The following example shows an application with two concurrently open instances of an iterator.

```
…
ResultSet myFunc(String empid)  // Method to open an iterator and get a resultSet
{
  MyIter iter;
  #sql iter = {SELECT * FROM EMPLOYEE WHERE EMPNO = :empid};
  return iter.getResultSet();
}

// An application can call this method to get a resultSet for each
// employee ID. The application can process each resultSet separately.
…
ResultSet rs1 = myFunc("000100");  // Get employee record for employee ID 000100
…
ResultSet rs2 = myFunc("000200");  // Get employee record for employee ID 000200
```

Figure 37. Example of opening more than one instance of an iterator in a single application

As with any other iterator, you need to remember to close this iterator after the last time you use it to prevent excessive storage consumption.

Using scrollable iterators in an SQLJ application

In addition to moving forward, one row at a time, through a result table, you might want to move backward or go directly to a specific row. The IBM Data Server Driver for JDBC and SQLJ provides this capability.

About this task

An iterator in which you can move forward, backward, or to a specific row is called a *scrollable iterator*. A scrollable iterator in SQLJ is equivalent to the result table of a database cursor that is declared as SCROLL.

Like a scrollable cursor, a scrollable iterator can be *insensitive* or *sensitive*. A sensitive scrollable iterator can be *static* or *dynamic*. Insensitive means that changes to the underlying table after the iterator is opened are not visible to the iterator. Insensitive iterators are read-only. Sensitive means that changes that the iterator or other processes make to the underlying table are visible to the iterator. Asensitive means that if the cursor is a read-only cursor, it behaves as an insensitive cursor. If it is not a read-only cursor, it behaves as a sensitive cursor.

If a scrollable iterator is static, the size of the result table and the order of the rows in the result table do not change after the iterator is opened. This means that you cannot insert into result tables, and if you delete a row of a result table, a delete hole occurs. If you update a row of the result table so that the row no longer qualifies for the result table, an update hole occurs. Fetching from a hole results in an `SQLException`.

Important: Like static scrollable cursors in any other language, SQLJ static scrollable iterators use declared temporary tables for their internal processing. This means that before you can execute any applications that contain static scrollable iterators, your database administrator needs to create a temporary database and temporary table spaces for those declared temporary tables.

If a scrollable iterator is dynamic, the size of the result table and the order of the rows in the result table can change after the iterator is opened. Rows that are inserted or deleted with INSERT and DELETE statements that are executed by the same application process are immediately visible. Rows that are inserted or deleted with INSERT and DELETE statements that are executed by other application processes are visible after the changes are committed.

Important: Db2 on Linux, UNIX, and Windows systems servers do not support dynamic scrollable cursors. You can use dynamic scrollable iterators in your SQLJ applications only if those applications access data on Db2 for z/OS servers, at Version 9 or later.

Procedure

To create and use a scrollable iterator, you need to follow these steps:

1. Specify an iterator declaration clause that includes the following clauses:

- `implements sqlj.runtime.Scrollable`

  This indicates that the iterator is scrollable.
- `with (sensitivity=`*`sensitivity-attribute`*`)` or `with (sensitivity=`*`sensitivity-attribute`*`, dynamic=true|false)`

  sensitivity-attribute indicates whether update or delete operations on the underlying table can be visible to the iterator. Possible values are sqlj.runtime.ResultSetIterator.SENSITIVE, sqlj.runtime.ResultSetIterator.INSENSITIVE, or sqlj.runtime.ResultSetIterator.ASENSITIVE. sqlj.runtime.ResultSetIterator.ASENSITIVE is the default.

  `dynamic=true|false` indicates whether the size of the result table or the order of the rows in the result table can change after the iterator is opened. The default value of dynamic is `false`.

The iterator can be a named or positioned iterator.

Example: The following iterator declaration clause declares a positioned, sensitive, dynamic, scrollable iterator:

```
#sql public iterator ByPos
  implements sqlj.runtime.Scrollable
  with (sensitivity=sqlj.runtime.ResultSetIterator.SENSITIVE, dynamic=true)
  (String);
```

Example: The following iterator declaration clause declares a named, insensitive, scrollable iterator:

```
#sql public iterator ByName
  implements sqlj.runtime.Scrollable
  with (sensitivity=sqlj.runtime.ResultSetIterator.INSENSITIVE) (String EmpNo);
```

Restriction: You cannot use a scrollable iterator to select columns with the following data types from a table on a Db2 on Linux, UNIX, and Windows systems server:

- LONG VARCHAR
- LONG VARGRAPHIC
- BLOB
- CLOB
- XML
- A distinct type that is based on any of the previous data types in this list
- A structured type

2. Create an iterator object, which is an instance of your iterator class.
3. If you want to give the SQLJ runtime environment a hint about the initial fetch direction, use the `setFetchDirection(int` *`direction`*`)` method. *direction* can be `FETCH_FORWARD` or `FETCH_REVERSE`. If you do not invoke `setFetchDirection`, the fetch direction is `FETCH_FORWARD`.
4. For each row that you want to access:

   For a named iterator, perform the following steps:

   a) Position the cursor using one of the methods listed in the following table.

Table 25. sqlj.runtime.Scrollable methods for positioning a scrollable cursor

Method	Positions the cursor
`first`"5.a.i" on page 150	On the first row of the result table
`last`"5.a.i" on page 150	On the last row of the result table
`previous`"5.a.i" on page 150,"5.a.ii" on page 150	On the previous row of the result table
`next`	On the next row of the result table

Table 25. sqlj.runtime.Scrollable methods for positioning a scrollable cursor (continued)

Method	Positions the cursor
`absolute(int n)` "5.a.i" on page 150, "5.a.iii" on page 150	If *n*>0, on row *n* of the result table. If *n*<0, and *m* is the number of rows in the result table, on row *m+n+1* of the result table.
`relative(int n)` "5.a.i" on page 150, "5.a.iv" on page 150	If *n*>0, on the row that is *n* rows after the current row. If *n*<0, on the row that is *n* rows before the current row. If *n*=0, on the current row.
`afterLast` "5.a.i" on page 150	After the last row in the result table
`beforeFirst` "5.a.i" on page 150	Before the first row in the result table

Notes:

i) This method does not apply to connections to IBM Informix.

ii) If the cursor is after the last row of the result table, this method positions the cursor on the last row.

iii) If the absolute value of *n* is greater than the number of rows in the result table, this method positions the cursor after the last row if *n* is positive, or before the first row if *n* is negative.

iv) Suppose that *m* is the number of rows in the result table and *x* is the current row number in the result table. If *n*>0 and *x*+*n*>*m*, the iterator is positioned after the last row. If *n*<0 and *x*+*n*<1, the iterator is positioned before the first row.

b) If you need to know the current cursor position, use the `getRow`, `isFirst`, `isLast`, `isBeforeFirst`, or `isAfterLast` method to obtain this information.

If you need to know the current fetch direction, invoke the `getFetchDirection` method.

c) Use accessor methods to retrieve the current row of the result table.

d) If update or delete operations by the iterator or by other means are visible in the result table, invoke the `getWarnings` method to check whether the current row is a hole.

For a positioned iterator, perform the following steps:

a) Use a FETCH statement with a fetch orientation clause to position the iterator and retrieve the current row of the result table. Table 26 on page 150 lists the clauses that you can use to position the cursor.

Table 26. FETCH clauses for positioning a scrollable cursor

Method	Positions the cursor
FIRST "5.a.i" on page 151	On the first row of the result table
LAST "5.a.i" on page 151	On the last row of the result table
PRIOR "5.a.i" on page 151, "5.a.ii" on page 151	On the previous row of the result table
NEXT	On the next row of the result table
ABSOLUTE(*n*) "5.a.i" on page 151, "5.a.iii" on page 151	If *n*>0, on row *n* of the result table. If *n*<0, and *m* is the number of rows in the result table, on row *m+n+1* of the result table.
RELATIVE(*n*) "5.a.i" on page 151, "5.a.iv" on page 151	If *n*>0, on the row that is *n* rows after the current row. If *n*<0, on the row that is *n* rows before the current row. If *n*=0, on the current row.
AFTER "5.a.i" on page 151, "5.a.v" on page 151	After the last row in the result table

Table 26. FETCH clauses for positioning a scrollable cursor (continued)

Method	Positions the cursor
BEFORE[“5.a.i” on page 151](#),[“5.a.v” on page 151](#)	Before the first row in the result table

Notes:

i) This value is not supported for connections to IBM Informix

ii) If the cursor is after the last row of the result table, this method positions the cursor on the last row.

iii) If the absolute value of *n* is greater than the number of rows in the result table, this method positions the cursor after the last row if *n* is positive, or before the first row if *n* is negative.

iv) Suppose that *m* is the number of rows in the result table and *x* is the current row number in the result table. If *n*>0 and *x*+*n*>*m*, the iterator is positioned after the last row. If *n*<0 and *x*+*n*<1, the iterator is positioned before the first row.

v) Values are not assigned to host expressions.

b) If update or delete operations by the iterator or by other means are visible in the result table, invoke the `getWarnings` method to check whether the current row is a hole.

5. Invoke the `close` method to close the iterator.

Example

The following code demonstrates how to use a named iterator to retrieve the employee number and last name from all rows from the employee table in reverse order. The numbers to the right of selected statements correspond to the previously-described steps.

```
#sql context Ctx;            // Create connection context class Ctx
#sql  iterator ScrollIter implements sqlj.runtime.Scrollable        1
  (String EmpNo, String LastName);
{
  …
  Ctx ctxt =
   new Ctx("jdbc:db2://sysmvs1.stl.ibm.com:5021/NEWYORK",
   userid,password,false);   // Create connection context object ctxt
                             // for the connection to NEWYORK
  ScrollIter scrliter;                                              2
  #sql [ctxt]
    scrliter={SELECT EMPNO, LASTNAME FROM EMPLOYEE};
  scrliter.afterLast();
  while (scrliter.previous())                                       4a
  {
    System.out.println(scrliter.EmpNo() + " "                       4c
      + scrliter.LastName());
  }
  scrliter.close();                                                 5
}
```

Related concepts

[“Data retrieval in SQLJ applications” on page 142](#)
SQLJ applications use a *result set iterator* to retrieve result sets. Like a cursor, a result set iterator can be non-scrollable or scrollable.

Related tasks

[“Using a positioned iterator in an SQLJ application” on page 144](#)
Use a positioned iterator to refer to columns in a result table by their position in the result set.

[“Using a named iterator in an SQLJ application” on page 143](#)

Use a named iterator to refer to each of the columns in a result table by name.

Calling stored procedures in SQLJ applications

To call a stored procedure, you use an executable clause that contains an SQL CALL statement.

About this task

You can execute the CALL statement with host identifier parameters. You can execute the CALL statement with literal parameters only if the data server on which the CALL statement runs supports execution of the CALL statement dynamically.

Procedure

The basic steps in calling a stored procedure are:

1. Assign values to input (IN or INOUT) parameters.
2. Call the stored procedure.
3. Process output (OUT or INOUT) parameters.
4. If the stored procedure returns multiple result sets, retrieve those result sets.

Example

The following code illustrates calling a stored procedure that has three input parameters and three output parameters. The numbers to the right of selected statements correspond to the previously-described steps.

```
String FirstName="TOM";            // Input parameters                1
String LastName="NARISINST";
String Address="IBM";
int CustNo;                        // Output parameters
String Mark;
String MarkErrorText;
…
#sql [myConnCtx] {CALL ADD_CUSTOMER(:IN FirstName,                     2
                            :IN LastName,
                            :IN Address,
                            :OUT CustNo,
                            :OUT Mark,
                            :OUT MarkErrorText)};
                                 // Call the stored procedure
System.out.println("Output parameters from ADD_CUSTOMER call: ");
System.out.println("Customer number for " + LastName + ": " + CustNo); 3
System.out.println(Mark);
If (MarkErrorText != null)
  System.out.println(" Error messages:" + MarkErrorText);
```

Figure 38. Example of calling a stored procedure in an SQLJ application

Related concepts

"Retrieving multiple result sets from a stored procedure in an SQLJ application" on page 152
Some stored procedures return one or more result sets to the calling program by including the DYNAMIC RESULT SETS *n* clause in the definition, with *n*>0, and opening cursors that are defined with the WITH RETURN clause. The calling program needs to retrieve the contents of those result sets.

Retrieving multiple result sets from a stored procedure in an SQLJ application

Some stored procedures return one or more result sets to the calling program by including the DYNAMIC RESULT SETS *n* clause in the definition, with *n*>0, and opening cursors that are defined with the WITH RETURN clause. The calling program needs to retrieve the contents of those result sets.

To retrieve the rows from those result sets, you execute these steps:

1. Acquire an execution context for retrieving the result set from the stored procedure.
2. Associate the execution context with the CALL statement for the stored procedure.

Do not use this execution context for any other purpose until you have retrieved and processed the last result set.

3. For each result set:
   a. Use the `ExecutionContext` method `getNextResultSet` to retrieve the result set.
   b. If you do not know the contents of the result set, use `ResultSetMetaData` methods to retrieve this information.
   c. Use an SQLJ result set iterator or JDBC `ResultSet` to retrieve the rows from the result set.

Result sets are returned to the calling program in the same order that their cursors are opened in the stored procedure. When there are no more result sets to retrieve, getNextResultSet returns a null value.

`getNextResultSet` has two forms:

```
getNextResultSet();
getNextResultSet(int current);
```

When you invoke the first form of `getNextResultSet`, SQLJ closes the currently-open result set and advances to the next result set. When you invoke the second form of `getNextResultSet`, the value of *current* indicates what SQLJ does with the currently-open result set before it advances to the next result set:

java.sql.Statement.CLOSE_CURRENT_RESULT
Specifies that the current `ResultSet` object is closed when the next `ResultSet` object is returned.

java.sql.Statement.KEEP_CURRENT_RESULT
Specifies that the current `ResultSet` object stays open when the next `ResultSet` object is returned.

java.sql.Statement.CLOSE_ALL_RESULTS
Specifies that all open `ResultSet` objects are closed when the next `ResultSet` object is returned.

The following code calls a stored procedure that returns multiple result sets. For this example, it is assumed that the caller does not know the number of result sets to be returned or the contents of those result sets. It is also assumed that autoCommit is false. The numbers to the right of selected statements correspond to the previously-described steps.

```
ExecutionContext execCtx=myConnCtx.getExecutionContext();      1
#sql [myConnCtx, execCtx] {CALL MULTRSSP()};                   2
            // MULTRSSP returns multiple result sets
ResultSet rs;
while ((rs = execCtx.getNextResultSet()) != null)              3a
{
  ResultSetMetaData rsmeta=rs.getMetaData();                   3b
  int numcols=rsmeta.getColumnCount();
  while (rs.next())                                            3c
  {
    for (int i=1; i<=numcols; i++)
    {
      String colval=rs.getString(i);
      System.out.println("Column " + i + "value is " + colval);
    }
  }
}
```

Figure 39. Retrieving result sets from a stored procedure

LOBs in SQLJ applications with the IBM Data Server Driver for JDBC and SQLJ

With the IBM Data Server Driver for JDBC and SQLJ, you can retrieve LOB data into `Clob` or `Blob` host expressions or update CLOB, BLOB, or DBCLOB columns from `Clob` or `Blob` host expressions. You can also declare iterators with `Clob` or `Blob` data types to retrieve data from CLOB, BLOB, or DBCLOB columns.

Retrieving or updating LOB data: To retrieve data from a BLOB column, declare an iterator that includes a data type of `Blob` or `byte[]`. To retrieve data from a CLOB or DBCLOB column, declare an iterator in which the corresponding column has a `Clob` data type.

To update data in a BLOB column, use a host expression with data type `Blob`. To update data in a CLOB or DBCLOB column, use a host expression with data type `Clob`.

Progressive streaming or LOB locators: In SQLJ applications, you can use progressive streaming, also known as dynamic data format, or LOB locators in the same way that you use them in JDBC applications.

Java data types for retrieving or updating LOB column data in SQLJ applications

When the deferPrepares property is set to true, and the IBM Data Server Driver for JDBC and SQLJ processes an uncustomized SQLJ statement that includes host expressions, the driver might need to do extra processing to determine data types. This extra processing can impact performance.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS, when the JDBC driver processes a CALL statement, the driver cannot determine the parameter data types.

When the JDBC driver cannot immediately determine the data type of a parameter that is used with a LOB column, you need to choose a parameter data type that is compatible with the LOB data type.

Input parameters for BLOB columns

For input parameters for BLOB columns, you can use either of the following techniques:

- Use a java.sql.Blob input variable, which is an exact match for a BLOB column:

```
java.sql.Blob blobData;
#sql {CALL STORPROC(:IN blobData)};
```

  Before you can use a java.sql.Blob input variable, you need to create a java.sql.Blob object, and then populate that object.

  For example, if you are using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, you can use the IBM Data Server Driver for JDBC and SQLJ-only method `com.ibm.db2.jcc.t2zos.DB2LobFactory.createBlob` to create a java.sql.Blob object and populate the object with byte[] data:

```
byte[] byteArray = {0, 1, 2, 3};
java.sql.Blob blobData =
  com.ibm.db2.jcc.t2zos.DB2LobFactory.createBlob(byteArray);
```

- Use an input parameter of type of `sqlj.runtime.BinaryStream`. A `sqlj.runtime.BinaryStream` object is compatible with a BLOB data type. For example:

```
java.io.ByteArrayInputStream byteStream =
  new java.io.ByteArrayInputStream(byteData);
int numBytes = byteData.length;
sqlj.runtime.BinaryStream binStream =
  new sqlj.runtime.BinaryStream(byteStream, numBytes);
#sql {CALL STORPROC(:IN binStream)};
```

  You cannot use this technique for INOUT parameters.

Output parameters for BLOB columns

For output or INOUT parameters for BLOB columns, you can use the following technique:

- Declare the output parameter or INOUT variable with a java.sql.Blob data type:

```
java.sql.Blob blobData = null;
#sql CALL STORPROC (:OUT blobData)};
```

```
java.sql.Blob blobData = null;
#sql CALL STORPROC (:INOUT blobData)};
```

Input parameters for CLOB columns

For input parameters for CLOB columns, you can use one of the following techniques:

- Use a java.sql.Clob input variable, which is an exact match for a CLOB column:

```
#sql CALL STORPROC(:IN clobData)};
```

  Before you can use a java.sql.Clob input variable, you need to create a java.sql.Clob object, and then populate that object.

  For example, if you are using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, you can use the IBM Data Server Driver for JDBC and SQLJ-only method `com.ibm.db2.jcc.t2zos.DB2LobFactory.createClob` to create a java.sql.Clob object and populate the object with String data:

```
String stringVal = "Some Data";
java.sql.Clob clobData =
  com.ibm.db2.jcc.t2zos.DB2LobFactory.createClob(stringVal);
```

- Use one of the following types of stream IN parameters:
  - A `sqlj.runtime.CharacterStream` input parameter:

```
java.lang.String charData;
java.io.StringReader reader = new java.io.StringReader(charData);
sqlj.runtime.CharacterStream charStream =
  new sqlj.runtime.CharacterStream (reader, charData.length);
#sql {CALL STORPROC(:IN charStream)};
```

  - A `sqlj.runtime.UnicodeStream` parameter, for Unicode UTF-16 data:

```
byte[] charDataBytes = charData.getBytes("UnicodeBigUnmarked");
java.io.ByteArrayInputStream byteStream =
  new java.io.ByteArrayInputStream(charDataBytes);
sqlj.runtime.UnicodeStream uniStream =
  new sqlj.runtime.UnicodeStream(byteStream, charDataBytes.length );
#sql {CALL STORPROC(:IN uniStream)};
```

  - A `sqlj.runtime.AsciiStream` parameter, for ASCII data:

```
byte[] charDataBytes = charData.getBytes("US-ASCII");
java.io.ByteArrayInputStream byteStream =
  new java.io.ByteArrayInputStream (charDataBytes);
sqlj.runtime.AsciiStream asciiStream =
  new sqlj.runtime.AsciiStream (byteStream, charDataBytes.length);
#sql {CALL STORPROC(:IN asciiStream)};
```

  For these calls, you need to specify the exact length of the input data. You cannot use this technique for INOUT parameters.

- Use a java.lang.String input parameter:

```
java.lang.String charData;
#sql {CALL STORPROC(:IN charData)};
```

Output parameters for CLOB columns

For output or INOUT parameters for CLOB columns, you can use one of the following techniques:

- Use a java.sql.Clob output variable, which is an exact match for a CLOB column:

```
java.sql.Clob clobData = null;
#sql CALL STORPROC(:OUT clobData)};
```

- Use a java.lang.String output variable:

```
java.lang.String charData = null;
#sql CALL STORPROC(:OUT charData)};
```

This technique should be used only if you know that the length of the retrieved data is less than or equal to 32KB. Otherwise, the data is truncated.

Output parameters for DBCLOB columns

DBCLOB output or INOUT parameters for stored procedures are not supported.

SQLJ and JDBC in the same application

You can combine SQLJ clauses and JDBC calls in a single program.

To do this effectively, you need to be able to do the following things:

- Use a JDBC `Connection` to build an SQLJ `ConnectionContext`, or obtain a JDBC `Connection` from an SQLJ `ConnectionContext`.
- Use an SQLJ iterator to retrieve data from a JDBC `ResultSet` or generate a JDBC `ResultSet` from an SQLJ iterator.

Building an SQLJ ConnectionContext from a JDBC Connection: To do that:

1. Execute an SQLJ connection declaration clause to create a `ConnectionContext` class.
2. Load the driver or obtain a `DataSource` instance.
3. Invoke the SQLJ `DriverManager.getConnection` or `DataSource.getConnection` method to obtain a JDBC `Connection`.
4. Invoke the `ConnectionContext` constructor with the `Connection` as its argument to create the `ConnectionContext` object.

Obtaining a JDBC Connection from an SQLJ ConnectionContext: To do this,

1. Execute an SQLJ connection declaration clause to create a `ConnectionContext` class.
2. Load the driver or obtain a `DataSource` instance.
3. Invoke the `ConnectionContext` constructor with the URL of the driver and any other necessary parameters as its arguments to create the `ConnectionContext` object.
4. Invoke the JDBC `ConnectionContext.getConnection` method to create the JDBC `Connection` object.

See "Connect to a data source using SQLJ" for more information on SQLJ connections.

Retrieving JDBC result sets using SQLJ iterators: Use the *iterator conversion statement* to manipulate a JDBC result set as an SQLJ iterator. The general form of an iterator conversion statement is:

```
#sql iterator={CAST :result-set};
```

Before you can successfully cast a result set to an iterator, the iterator must conform to the following rules:

- The iterator must be declared as public.
- If the iterator is a positioned iterator, the number of columns in the result set must match the number of columns in the iterator. In addition, the data type of each column in the result set must match the data type of the corresponding column in the iterator.
- If the iterator is a named iterator, the name of each accessor method must match the name of a column in the result set. In addition, the data type of the object that an accessor method returns must match the data type of the corresponding column in the result set.

The code in Figure 40 on page 157 builds and executes a query using a JDBC call, executes an iterator conversion statement to convert the JDBC result set to an SQLJ iterator, and retrieves rows from the result table using the iterator.

```
#sql public iterator ByName(String LastName, Date HireDate);     1
public void HireDates(ConnectionContext connCtx, String whereClause)
{

  ByName nameiter;           // Declare object of ByName class
  Connection conn=connCtx.getConnection();
                             // Create JDBC connection
  Statement stmt = conn.createStatement();                        2
  String query = "SELECT LASTNAME, HIREDATE FROM EMPLOYEE";
  query+=whereClause;   // Build the query
  ResultSet rs = stmt.executeQuery(query);                        3
  #sql [connCtx] nameiter = {CAST :rs};                           4
  while (nameiter.next())
  {
    System.out.println( nameiter.LastName() + " was hired on "
      + nameiter.HireDate());

  }
  nameiter.close();                                               5
  stmt.close();
}
```

Figure 40. Converting a JDBC result set to an SQLJ iterator

Notes to Figure 40 on page 157:

Note	Description
1	This SQLJ clause creates the named iterator class ByName, which has accessor methods LastName() and HireDate() that return the data from result table columns LASTNAME and HIREDATE.
2	This statement and the following two statements build and prepare a query for dynamic execution using JDBC.
3	This JDBC statement executes the SELECT statement and assigns the result table to result set rs.
4	This iterator conversion clause converts the JDBC `ResultSet` rs to SQLJ iterator nameiter, and the following statements use nameiter to retrieve values from the result table.
5	The `nameiter.close()` method closes the SQLJ iterator and JDBC `ResultSet` rs.

Generating JDBC ResultSets from SQLJ iterators: Use the getResultSet method to generate a JDBC `ResultSet` from an SQLJ iterator. Every SQLJ iterator has a `getResultSet` method. After you access the `ResultSet` that underlies an iterator, you need to fetch rows using only the `ResultSet`.

The code in Figure 41 on page 157 generates a positioned iterator for a query, converts the iterator to a result set, and uses JDBC methods to fetch rows from the table.

```
#sql iterator EmpIter(String, java.sql.Date);
{
…
  EmpIter iter=null;
  #sql [connCtx] iter=
    {SELECT LASTNAME, HIREDATE FROM EMPLOYEE};                    1
  ResultSet rs=iter.getResultSet();                               2
  while (rs.next())                                               3
  { System.out.println(rs.getString(1) + " was hired in " +
      rs.getDate(2));
  }
  rs.close();                                                     4
}
```

Figure 41. Converting an SQLJ iterator to a JDBC ResultSet

Notes to Figure 41 on page 157:

Note	Description
1	This SQLJ clause executes the SELECT statement, constructs an iterator object that contains the result table for the SELECT statement, and assigns the iterator object to variable iter.
2	The getResultSet() method accesses the `ResultSet` that underlies iterator iter.
3	The JDBC getString() and getDate() methods retrieve values from the `ResultSet`. The next() method moves the cursor to the next row in the `ResultSet`.
4	The `rs.close()` method closes the SQLJ iterator as well as the `ResultSet`.

Rules and restrictions for using JDBC ResultSets in SQLJ applications: When you write SQLJ applications that include JDBC result sets, observe the following rules and restrictions:

- Before you can access the columns of a remote table by name, through either a named iterator or an iterator that is converted to a JDBC `ResultSet` object, the Db2 for z/OS DESCSTAT subsystem parameter must be set to YES.
- You cannot cast a `ResultSet` to an SQLJ iterator if the `ResultSet` and the iterator have different holdability attributes.

  A JDBC `ResultSet` or an SQLJ iterator can remain open after a COMMIT operation. For a JDBC `ResultSet`, this characteristic is controlled by the IBM Data Server Driver for JDBC and SQLJ property `resultSetHoldability`. For an SQLJ iterator, this characteristic is controlled by the `with holdability` parameter of the iterator declaration. Casting a `ResultSet` that has holdability to an SQLJ iterator that does not, or casting a `ResultSet` that does not have holdability to an SQLJ iterator that does, is not supported.
- Close the iterator or the underlying `ResultSet` object as soon as the program no longer uses the iterator or `ResultSet`, and before the end of the program.

  Closing the iterator also closes the `ResultSet` object. Closing the `ResultSet` object also closes the iterator object. In general, it is best to close the object that is used last.
- For the IBM Data Server Driver for JDBC and SQLJ, which supports scrollable iterators and scrollable and updatable `ResultSet` objects, the following restrictions apply:
  - Scrollable iterators have the same restrictions as their underlying JDBC `ResultSet` objects.
  - You cannot cast a JDBC `ResultSet` that is not updatable to an SQLJ iterator that is updatable.

Related reference
DESCRIBE FOR STATIC field (DESCSTAT subsystem parameter) (Db2 Installation and Migration)

Controlling the execution of SQL statements in SQLJ

You can use selected methods of the SQLJ `ExecutionContext` class to control or monitor the execution of SQL statements.

Procedure

To use `ExecutionContext` methods, follow these steps:

1. Acquire the default execution context from the connection context.

   There are two ways to acquire an execution context:

   - Acquire the default execution context from the connection context. For example:

     ```
     ExecutionContext execCtx = connCtx.getExecutionContext();
     ```

   - Create a new execution context by invoking the constructor for `ExecutionContext`. For example:

     ```
     ExecutionContext execCtx=new ExecutionContext();
     ```

2. Associate the execution context with an SQL statement.

To do that, specify an execution context after the connection context in the execution clause that contains the SQL statement.

3. Invoke `ExecutionContext` methods.

   Some ExecutionContext methods are applicable before the associated SQL statement is executed, and some are applicable only after their associated SQL statement is executed.

   For example, you can use method `getUpdateCount` to count the number of rows that are deleted by a DELETE statement after you execute the DELETE statement.

Example

The following code demonstrates how to acquire an execution context, and then use the `getUpdateCount` method on that execution context to determine the number of rows that were deleted by a DELETE statement. The numbers to the right of selected statements correspond to the previously-described steps.

```
ExecutionContext execCtx=new ExecutionContext();                          1
#sql [connCtx, execCtx] {DELETE FROM EMPLOYEE WHERE SALARY > 10000};      2
System.out.println("Deleted " + execCtx.getUpdateCount() + " rows");      3
```

Related tasks

"Handling an SQLWarning under the IBM Data Server Driver for JDBC and SQLJ" on page 113
Unlike SQL errors, SQL warnings do not cause JDBC methods to throw exceptions. Instead, the `Connection`, `Statement`, `PreparedStatement`, `CallableStatement`, and `ResultSet` classes contain `getWarnings` methods, which you need to invoke after you execute SQL statements to determine whether any SQL warnings were generated.

"Handling SQL warnings in an SQLJ application" on page 173
Other than a +100 SQL error code on a SELECT INTO statement, warnings from the data server do not throw SQLExceptions. To handle warnings from the data server, you need to give the program access to the `java.sql.SQLWarning` class.

"Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ" on page 111
As in all Java programs, error handling for JDBC applications is done using `try/catch` blocks. Methods throw exceptions when an error occurs, and the code in the `catch` block handles those exceptions.

ROWIDs in SQLJ with the IBM Data Server Driver for JDBC and SQLJ

Db2 for z/OS and Db2 for IBM i support the ROWID data type for a column in a table. A ROWID is a value that uniquely identifies a row in a table.

Although IBM Informix also supports rowids, those rowids have the INTEGER data type. You can select an IBM Informix rowid column into a variable with a four-byte integer data type.

If you use columns with the ROWID data type in SQLJ programs, you need to customize those programs.

JDBC 4.0 includes interface `java.sql.RowId` that you can use in iterators and in CALL statement parameters. If you do not have JDBC 4.0, you can use the IBM Data Server Driver for JDBC and SQLJ-only class `com.ibm.db2.jcc.DB2RowID`. For an iterator, you can also use the byte[] object type to retrieve ROWID values.

The following code shows an example of an iterator that is used to select values from a ROWID column:

```
#sql iterator PosIter(int,String,java.sql.RowId);
                                // Declare positioned iterator
                                // for retrieving ITEM_ID (INTEGER),
                                // ITEM_FORMAT (VARCHAR), and ITEM_ROWID (ROWID)
                                // values from table ROWIDTAB
{
  PosIter positrowid;           // Declare object of PosIter class
  java.sql.RowId rowid = null;
  int id = 0;
  String i_fmt = null;
                                // Declare host expressions
  #sql [ctxt] positrowid =
    {SELECT ITEM_ID, ITEM_FORMAT, ITEM_ROWID FROM ROWIDTAB
       WHERE ITEM_ID=3};
                                // Assign the result table of the SELECT
                                // to iterator object positrowid
  #sql {FETCH :positrowid INTO :id, :i_fmt, :rowid};
                                // Retrieve the first row
  while (!positrowid.endFetch())
                                // Check whether the FETCH returned a row
    {System.out.println("Item ID " + id + " Item format " +
       i_fmt + " Item ROWID ");
       MyUtilities.printBytes(rowid.getBytes());
                           // Use the getBytes method to
                           // convert the value to bytes for printing.
                           // Call a user-defined method called
                           // printBytes (not shown) to print
                           // the value.
       #sql {FETCH :positrowid INTO :id, :i_fmt, :rowid};
                                // Retrieve the next row
    }
  positrowid.close();           // Close the iterator
}
```

Figure 42. Example of using an iterator to retrieve ROWID values

The following code shows an example of calling a stored procedure that takes three ROWID parameters: an IN parameter, an OUT parameter, and an INOUT parameter.

```
java.sql.RowId in_rowid = rowid;
java.sqlRowId out_rowid = null;
java.sql.RowId inout_rowid = rowid;
                                    // Declare an IN, OUT, and
                                    // INOUT ROWID parameter
…
#sql [myConnCtx] {CALL SP_ROWID(:IN in_rowid,
                              :OUT out_rowid,
                              :INOUT inout_rowid)};
                                    // Call the stored procedure
System.out.println("Parameter values from SP_ROWID call: ");
System.out.println("OUT parameter value ");
MyUtilities.printBytes(out_rowid.getBytes());
                           // Use the getBytes method to
                           // convert the value to bytes for printing
                           // Call a user-defined method called
                           // printBytes (not shown) to print
                           // the value.
System.out.println("INOUT parameter value ");
MyUtilities.printBytes(inout_rowid.getBytes());
```

Figure 43. Example of calling a stored procedure with a ROWID parameter

TIMESTAMP WITH TIME ZONE values in SQLJ applications

Db2 for z/OS supports table columns with the TIMESTAMP WITH TIME ZONE data type. IBM Data Server Driver for JDBC and SQLJ supports update into and retrieval from a column with the TIMESTAMP WITH TIME ZONE data type in SQLJ programs.

When you update or retrieve a TIMESTAMP WITH TIME ZONE value, or call a stored procedure with a TIMESTAMP WITH TIME ZONE parameter, you need to use host variables that are `com.ibm.db2.jcc.DBTimestamp` objects to retain the time zone information. If you use `java.sql.Timestamp` objects to pass TIMESTAMP WITH TIME ZONE values to and from the data server, you lose the time zone information.

Because the com.ibm.db2.jcc.DBTimestamp class is a IBM Data Server Driver for JDBC and SQLJ-only class, if you run an uncustomized SQLJ application that uses com.ibm.db2.jcc.DBTimestamp objects, the application receives an SQLException.

Examples

Suppose that table TSTABLE has a single column, TSCOL, which has data type TIMESTAMP WITH TIME ZONE. The following code assigns a timestamp value with a time zone to the column, and retrieves the value from the column.

```
#sql iterator TSIter(com.ibm.db2.jcc.DBTimestamp TSVar);
{
  …
  java.util.TimeZone esttz = java.util.TimeZone.getTimeZone("EST");
                                  // Set the time zone to UTC-5
  java.util.Calendar estcal= java.util.Calendar.getInstance(esttz);
                                  // Create a calendar instance
                                  //  with the EST time zone
  java.sql.Timestamp ts =
      java.sql.Timestamp.valueOf("2009-02-27 21:22:33.444444");
                                  // Initialize a timestamp object
                                  //  with the datetime value that you
                                  //  want to put in the table
  com.ibm.db2.jcc.DBTimestamp dbts =
    new com.ibm.db2.jcc.DBTimestamp(ts,estcal);
                                  // Create a datetime object that
                                  //  includes the time zone
  #sql[ctx] {INSERT INTO TSTABLE (TSCOL) VALUES (:dbts)};
                                  // Insert the datetime object in
                                  //  the table
  #sql[ctx] {COMMIT};

  TSIter iter = null;
  #sql [ctx] iter = {SELECT TSCOL FROM TSTABLE};
                                  // Assign the result table of the SELECT
  while (iter.next()) {
    System.out.println ("Timestamp = " +
      ((com.ibm.db2.jcc.DBTimestamp)iter.TSVar()).toDBString(true));
                                  // Use accessor method TSVar to retrieve
                                  //  the TIMESTAMP WITH TIME ZONE value,
                                  //  cast it to a DBTimestamp value,
                                  //  and retrieve its string representation.
                                  //  Value retrieved:
                                  //  2009-02-27 21:22:33.444444-05:00
  }
}
```

Suppose that stored procedure TSSP has a single INOUT parameter, TSPARM, which has data type TIMESTAMP WITH TIME ZONE. The following code calls the stored procedure with a timestamp value that includes a time zone, and retrieves a parameter value with a timestamp value that includes a time zone.

```
{
  …
  java.util.TimeZone esttz = java.util.TimeZone.getTimeZone("EST");
                                  // Set the time zone to UTC-5
  java.util.Calendar estcal= java.util.Calendar.getInstance(esttz);
                                  // Create a calendar instance
                                  //  with the EST time zone
  java.sql.Timestamp ts =
      java.sql.Timestamp.valueOf("2009-02-27 21:22:33.444444");
                                  // Initialize a timestamp object
                                  //  with the timestamp value that you
                                  //  want to pass to the stored procedure
  com.ibm.db2.jcc.DBTimestamp dbts =
    new com.ibm.db2.jcc.DBTimestamp(ts,estcal);
                                  // Create a timestamp object that
                                  //  includes the time zone to
                                  //  pass to the stored procedure
  #sql[ctx] { CALL TSSP (:INOUT dbts) };
  System.out.println ("Output parameter: " + dbts.toDBString (true));
                                  // Call the stored procedure with
                                  //  the timestamp value as input,
                                  //  and retrieve a timestamp value
                                  //  with a time zone in the same
```

```
                                    //  parameter
}
```

Distinct types in SQLJ applications

In an SQLJ program, you can create a distinct type using the CREATE DISTINCT TYPE statement in an executable clause.

You can also use CREATE TABLE in an executable clause to create a table that includes a column of that type. When you retrieve data from a column of that type, or update a column of that type, you use Java host variables or expressions with data types that correspond to the built-in types on which the distinct types are based.

The following example creates a distinct type that is based on an INTEGER type, creates a table with a column of that type, inserts a row into the table, and retrieves the row from the table:

```
String empNumVar;
int shoeSizeVar;
…
#sql [myConnCtx] {CREATE DISTINCT TYPE SHOESIZE AS INTEGER WITH COMPARISONS};
                                          // Create distinct type
#sql [myConnCtx] {COMMIT}; // Commit the create
#sql [myConnCtx] {CREATE TABLE EMP_SHOE
  (EMPNO CHAR(6), EMP_SHOE_SIZE SHOESIZE)};
                                          // Create table using distinct type
#sql [myConnCtx] {COMMIT}; // Commit the create
#sql [myConnCtx] {INSERT INTO EMP_SHOE
  VALUES('000010',6)};                    // Insert a row in the table
#sql [myConnCtx] {COMMIT}; // Commit the INSERT
#sql [myConnCtx] {SELECT EMPNO, EMP_SHOE_SIZE
  INTO :empNumVar, :shoeSizeVar
  FROM EMP_SHOE};                         // Retrieve the row
System.out.println("Employee number: " + empNumVar +
  " Shoe size: " + shoeSizeVar);
```

Figure 44. Defining and using a distinct type

Related reference

CREATE TYPE (distinct) (Db2 SQL)

Savepoints in SQLJ applications

Under the IBM Data Server Driver for JDBC and SQLJ, you can include any form of the SQL SAVEPOINT statement in your SQLJ program.

An SQL savepoint represents the state of data and schemas at a particular point in time within a unit of work. SQL statements exist to set a savepoint, release a savepoint, and restore data and schemas to the state that the savepoint represents.

The following example demonstrates how to set a savepoint, roll back to the savepoint, and release the savepoint.

Figure 45. Setting, rolling back to, and releasing a savepoint in an SQLJ application

```
#sql context Ctx;             // Create connection context class Ctx
String empNumVar;
int shoeSizeVar;
…
try {                         // Load the JDBC driver
  Class.forName("com.ibm.db2.jcc.DB2Driver");
}
catch (ClassNotFoundException e) {
   e.printStackTrace();
}
Connection jdbccon=
  DriverManager.getConnection("jdbc:db2://sysmvs1.stl.ibm.com:5021/NEWYORK",
    userid,password);
                              // Create JDBC connection object jdbccon
jdbccon.setAutoCommit(false); // Do not autocommit
Ctx ctxt=new Ctx(jdbccon);
                              // Create connection context object myConnCtx
```

```
                                // for the connection to NEWYORK
…                               // Perform some SQL
#sql [ctxt] {COMMIT};           // Commit the transaction
                                // Commit the create
#sql [ctxt]
  {INSERT INTO EMP_SHOE VALUES ('000010', 6)};
                                // Insert a row
#sql [ctxt]
  {SAVEPOINT SVPT1 ON ROLLBACK RETAIN CURSORS};
                                // Create a savepoint
…
#sql [ctxt]
  {INSERT INTO EMP_SHOE VALUES ('000020', 10)};
                                // Insert another row
#sql [ctxt] {ROLLBACK TO SAVEPOINT SVPT1};
                                // Roll back work to the point
                                //  after the first insert
…
#sql [ctxt] {RELEASE SAVEPOINT SVPT1};
                                // Release the savepoint
ctx.close();                    // Close the connection context
```

XML data in SQLJ applications

In SQLJ applications, you can store data in XML columns and retrieve data from XML columns.

In Db2 tables, the XML built-in data type is used to store XML data in a column as a structured set of nodes in a tree format.

SQLJ applications can send XML data to the data server or retrieve XML data from the data server in one of the following forms:

- As textual XML data
- As binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports it

In SQLJ applications, you can:

- Store an entire XML document in an XML column using INSERT, UPDATE, or MERGE statements.
- Retrieve an entire XML document from an XML column using single-row SELECT statements or iterators.
- Retrieve a sequence from a document in an XML column by using the SQL XMLQUERY function to retrieve the sequence in the database, and then using single-row SELECT statements or iterators to retrieve the serialized XML string data into an application variable.
- You can update or retrieve XML data as textual XML data. Alternatively, for connections to a data server that supports binary XML data, you can update or retrieve XML data as binary XML data.

  For data retrieval, you use the `Datasource` or `Connection` property xmlFormat to control whether the format of the retrieved data is textual XML or binary XML.

  For update of data in XML columns, xmlFormat has no effect. If the input data is binary XML data, and the data server does not support binary XML data, the input data is converted to textual XML data. Otherwise, no conversion occurs.

  The format of XML data is transparent to the application. Storage and retrieval of binary XML data on a Db2 for z/OS data server requires version 4.9 or later of the IBM Data Server Driver for JDBC and SQLJ. Storage and retrieval of binary XML data on a Db2 on Linux, UNIX, and Windows systems data server requires version 4.11 or later of the IBM Data Server Driver for JDBC and SQLJ.

JDBC 4.0 `java.sql.SQLXML` objects can be used to retrieve and update data in XML columns. Invocations of metadata methods, such as `ResultSetMetaData.getColumnType` return the integer value `java.sql.Types.SQLXML` for an XML column type.

Related concepts

“XML data retrieval in SQLJ applications” on page 165

When you retrieve data from XML columns of a database table in an SQLJ application, the output data must be explicitly or implicitly serialized.

"XML column updates in SQLJ applications" on page 164
In an SQLJ application, you can update or insert data into XML columns of a table at a Db2 data server using XML textual data. You can update or insert data into XML columns of a table using binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports binary XML data.

XML column updates in SQLJ applications

In an SQLJ application, you can update or insert data into XML columns of a table at a Db2 data server using XML textual data. You can update or insert data into XML columns of a table using binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports binary XML data.

The host expression data types that you can use to update XML columns are:

- java.sql.SQLXML (requires an SDK for Java Version 6 or later, and the IBM Data Server Driver for JDBC and SQLJ version 4.0 or later)
- com.ibm.db2.jcc.DB2Xml (deprecated)
- String
- byte
- Blob
- Clob
- sqlj.runtime.AsciiStream
- sqlj.runtime.BinaryStream
- sqlj.runtime.CharacterStream

The encoding of XML data can be derived from the data itself, which is known as *internally encoded* data, or from external sources, which is known as *externally encoded* data. XML data that is sent to the database server as binary data is treated as internally encoded data. XML data that is sent to the data source as character data is treated as externally encoded data. The external encoding is the default encoding for the JVM.

External encoding for Java applications is always Unicode encoding.

Externally encoded data can have internal encoding. That is, the data might be sent to the data source as character data, but the data contains encoding information. The data source handles incompatibilities between internal and external encoding as follows:

- If the data source is Db2 on Linux, UNIX, and Windows systems, the data source generates an error if the external and internal encoding are incompatible, unless the external and internal encoding are Unicode. If the external and internal encoding are Unicode, the data source ignores the internal encoding.
- If the data source is Db2 for z/OS, the data source ignores internal encoding.

Character data in XML columns is stored in UTF-8 encoding.

Example: Suppose that you use the following statement to insert data from String host expression xmlString into an XML column in a table. xmlString is a character type, so its external encoding is used, whether or not it has an internal encoding specification.

```
#sql [ctx] {INSERT INTO CUSTACC VALUES (1, :xmlString)};
```

Example: Suppose that you copy the data from xmlString into a byte array with CP500 encoding. The data contains an XML declaration with an encoding declaration for CP500. Then you insert the data from the byte[] host expression into an XML column in a table.

```
byte[] xmlBytes = xmlString.getBytes("CP500");
#sql[ctx] {INSERT INTO CUSTACC VALUES (4, :xmlBytes)};
```

A byte string is considered to be internally encoded data. The data is converted from its internal encoding scheme to UTF-8, if necessary, and stored in its hierarchical format on the data source.

Example: Suppose that you copy the data from xmlString into a byte array with US-ASCII encoding. Then you construct an sqlj.runtime.AsciiStream host expression, and insert data from the sqlj.runtime.AsciiStream host expression into an XML column in a table on a data source.

```
byte[] b = xmlString.getBytes("US-ASCII");
java.io.ByteArrayInputStream xmlAsciiInputStream =
  new java.io.ByteArrayInputStream(b);
sqlj.runtime.AsciiStream sqljXmlAsciiStream =
  new sqlj.runtime.AsciiStream(xmlAsciiInputStream,  b.length);
#sql[ctx] {INSERT INTO CUSTACC VALUES (4, :sqljXmlAsciiStream)};
```

sqljXmlAsciiStream is a stream type, so its internal encoding is used. The data is converted from its internal encoding to UTF-8 encoding and stored in its hierarchical form on the data source.

Example: sqlj.runtime.CharacterStream host expression: Suppose that you construct an sqlj.runtime.CharacterStream host expression, and insert data from the sqlj.runtime.CharacterStream host expression into an XML column in a table.

```
java.io.StringReader xmlReader =
  new java.io.StringReader(xmlString);
sqlj.runtime.CharacterStream sqljXmlCharacterStream =
  new sqlj.runtime.CharacterStream(xmlReader,  xmlString.length());
#sql [ctx] {INSERT INTO CUSTACC VALUES (4, :sqljXmlCharacterStream)};
```

sqljXmlCharacterStream is a character type, so its external encoding is used, whether or not it has an internal encoding specification.

Example: Suppose that you retrieve a document from an XML column into a java.sql.SQLXML host expression, and insert the data into an XML column in a table.

```
java.sql.ResultSet rs = s.executeQuery ("SELECT * FROM CUSTACC");
rs.next();
java.sql.SQLXML xmlObject = (java.sql.SQLXML)rs.getObject(2);
#sql [ctx] {INSERT INTO CUSTACC VALUES (6, :xmlObject)};
```

After you retrieve the data it is still in UTF-8 encoding, so when you insert the data into another XML column, no conversion occurs.

Example: Suppose that you retrieve a document from an XML column into a com.ibm.db2.jcc.DB2Xml host expression, and insert the data into an XML column in a table.

```
java.sql.ResultSet rs = s.executeQuery ("SELECT * FROM CUSTACC");
rs.next();
com.ibm.db2.jcc.DB2Xml xmlObject = (com.ibm.db2.jcc.DB2Xml)rs.getObject(2);
#sql [ctx] {INSERT INTO CUSTACC VALUES (6, :xmlObject)};
```

After you retrieve the data it is still in UTF-8 encoding, so when you insert the data into another XML column, no conversion occurs.

XML data retrieval in SQLJ applications

When you retrieve data from XML columns of a database table in an SQLJ application, the output data must be explicitly or implicitly serialized.

The host expression or iterator data types that you can use to retrieve data from XML columns are:

- java.sql.SQLXML (requires an SDK for Java Version 6 or later, and the IBM Data Server Driver for JDBC and SQLJ version 4.0 or later)

- com.ibm.db2.jcc.DB2Xml (deprecated)
- String
- byte[]
- sqlj.runtime.AsciiStream
- sqlj.runtime.BinaryStream
- sqlj.runtime.CharacterStream

If the application does not call the XMLSERIALIZE function before data retrieval, the data is converted from UTF-8 to the external application encoding for the character data types, or the internal encoding for the binary data types. No XML declaration is added. If the host expression is an object of the java.sql.SQLXML or com.ibm.db2.jcc.DB2Xml type, you need to call an additional method to retrieve the data from this object. The method that you call determines the encoding of the output data and whether an XML declaration with an encoding specification is added.

The following table lists the methods that you can call to retrieve data from a java.sql.SQLXML or a com.ibm.db2.jcc.DB2Xml object, and the corresponding output data types and type of encoding in the XML declarations.

Table 27. SQLXML and DB2Xml methods, data types, and added encoding specifications

Method	Output data type	Type of XML internal encoding declaration added
SQLXML.getBinaryStream	InputStream	None
SQLXML.getCharacterStream	Reader	None
SQLXML.getSource	Source	None
SQLXML.getString	String	None
DB2Xml.getDB2AsciiStream	InputStream	None
DB2Xml.getDB2BinaryStream	InputStream	None
DB2Xml.getDB2Bytes	byte[]	None
DB2Xml.getDB2CharacterStream	Reader	None
DB2Xml.getDB2String	String	None
DB2Xml.getDB2XmlAsciiStream	InputStream	US-ASCII
DB2Xml.getDB2XmlBinaryStream	InputStream	Specified by `getDB2XmlBinaryStream` *targetEncoding* parameter
DB2Xml.getDB2XmlBytes	byte[]	Specified by DB2Xml.getDB2XmlBytes *targetEncoding* parameter
DB2Xml.getDB2XmlCharacterStream	Reader	ISO-10646-UCS-2
DB2Xml.getDB2XmlString	String	ISO-10646-UCS-2

If the application executes the XMLSERIALIZE function on the data that is to be returned, after execution of the function, the data has the data type that is specified in the XMLSERIALIZE function, not the XML data type. Therefore, the driver handles the data as the specified type and ignores any internal encoding declarations.

Example: Suppose that you retrieve data from an XML column into a String host expression.

```
#sql iterator  XmlStringIter (int, String);
#sql [ctx] siter = {SELECT C1, CADOC from CUSTACC};
#sql {FETCH :siter INTO :row, :outString};
```

The String type is a character type, so the data is converted from UTF-8 to the external encoding, which is the default JVM encoding, and returned without any XML declaration.

Example: Suppose that you retrieve data from an XML column into a byte[] host expression.

```
#sql iterator  XmlByteArrayIter (int, byte[]);
XmlByteArrayIter biter = null;
#sql [ctx] biter =  {SELECT c1, CADOC from CUSTACC};
#sql {FETCH :biter INTO :row, :outBytes};
```

The byte[] type is a binary type, so no data conversion from UTF-8 encoding occurs, and the data is returned without any XML declaration.

Example: Suppose that you retrieve a document from an XML column into a java.sql.SQLXML host expression, but you need the data in a binary stream.

```
#sql iterator  SqlXmlIter (int, java.sql.SQLXML);
SqlXmlIter SQLXMLiter = null;
java.sql.SQLXML outSqlXml = null;
#sql [ctx] SqlXmlIter = {SELECT c1, CADOC from CUSTACC};
#sql {FETCH :SqlXmlIter INTO :row, :outSqlXml};
java.io.InputStream XmlStream = outSqlXml.getBinaryStream();
```

The FETCH statement retrieves the data into the SQLXML object in UTF-8 encoding. The SQLXML.getBinaryStream stores the data in a binary stream.

Example: Suppose that you retrieve a document from an XML column into a com.ibm.db2.jcc.DB2Xml host expression, but you need the data in a byte string with an XML declaration that includes an internal encoding specification for UTF-8.

```
#sql iterator  DB2XmlIter (int, com.ibm.db2.jcc.DB2Xml);
DB2XmlIter db2xmliter = null;
com.ibm.db2.jcc.DB2Xml outDB2Xml = null;
#sql [ctx] db2xmliter = {SELECT c1, CADOC from CUSTACC};
#sql {FETCH :db2xmliter INTO :row, :outDB2Xml};
byte[] byteArray = outDB2XML.getDB2XmlBytes("UTF-8");
```

The FETCH statement retrieves the data into the DB2Xml object in UTF-8 encoding. The getDB2XmlBytes method with the UTF-8 argument adds an XML declaration with a UTF-8 encoding specification and stores the data in a byte array.

XMLCAST in SQLJ applications

Before you can use XMLCAST to cast a host variable to the XML data type in an SQLJ application, you need to cast the host variable to the corresponding SQL data type.

Example: The following code demonstrates a situation in which it is necessary to cast a String host variable to an SQL character type, such as VARCHAR, before you use XMLCAST to cast the value to the XML data type.

```
String xmlresult = null;
String varchar_hv = "San Jose";
…
#sql [con] {SELECT XMLCAST(CAST(:varchar_hv AS VARCHAR(32)) AS XML) INTO
  :xmlresult FROM SYSIBM.SYSDUMMY1};
```

Inserting data from file reference variables into tables in SQLJ applications

You can use file reference variable objects with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9 or later to stream LOB or XML input data.

Before you begin

You need to store your LOB or XML input data in HFS files.

About this task

Use of file reference variables eliminates the need to materialize the LOB or XML data in memory before the data is stored in tables.

Procedure

To use file reference variables to store LOB or XML data in tables, follow these steps:

1. Execute constructors for file reference variable objects of the appropriate types.

   The following table lists the types of data in the input files and the appropriate constructors.

Input data type	Constructor
BLOB	com.ibm.db2.jcc.DB2BlobFileReference
CLOB	com.ibm.db2.jcc.DB2ClobFileReference
XML AS BLOB	com.ibm.db2.jcc.DB2XmlAsBlobFileReference
XML AS CLOB	com.ibm.db2.jcc.DB2XmlAsClobFileReference

   The first parameter in each constructor must specify the absolute path name for an existing HFS file.
2. Execute an INSERT statement with the file reference variable object as the input host variable.

Example

Suppose that a table is defined like this:

```
CREATE TABLE TEST02TB (
  RECID INTEGER,
  CLOBCOL CLOB(100M),
  BLOBCOL(200M),
  XMLCOL XML)
```

The following code uses file reference variables to insert a CLOB value, a BLOB value, and an XML AS BLOB value into the table. The numbers to the right of selected statements correspond to the previously described steps.

```
…
com.ibm.db2.jcc.DB2ClobFileReference clobFileRef =                          1
  new com.ibm.db2.jcc.DB2ClobFileReference("/u/usrt001/jcc/test/TEXT.FILE","Cp037");
com.ibm.db2.jcc.DB2BlobFileReference blobFileRef =
  new com.ibm.db2.jcc.DB2BlobFileReference("/u/usrt001/jcc/test/BINARY.FILE");
com.ibm.db2.jcc.DB2XmlAsBlobFileReference xmlAsBlobFileRef =
  new com.ibm.db2.jcc.DB2XmlAsBlobFileReference(
  "/u/usrt001/jcc/test/XML.FILE");
                          // Execute constructors for the file reference
                          // variable objects
#sql [ctx] {"INSERT INTO TEST03TB(RECID,CLOBCOL,BLOBCOL,XMLCOL)             2
  VALUES('003',:clobFileRef,:blobFileRef,:xmlAsBlobFileRef)};
```

SQLJ utilization of SDK for Java Version 5 function

Your SQLJ applications can use a number of functions that were introduced with the SDK for Java Version 5.

Static import

The static import construct lets you access static members without qualifying those members with the name of the class to which they belong. For SQLJ applications, this means that you can use static members in host expressions without qualifying them.

Example: Suppose that you want to declare a host expression of this form:

```
double r = cos(PI * E);
```

cos, PI, and E are members of the `java.lang.Math` class. To declare r without explicitly qualifying cos, PI, and E, include the following static import statement in your program:

```
import static java.lang.Math.*;
```

Annotations

Java annotations are a means for adding metadata to Java programs that can also affect the way that those programs are treated by tools and libraries. Annotations are declared with annotation type declarations, which are similar to interface declarations. Java annotations can appear in the following types of classes or interfaces:

- Class declaration
- Interface declaration
- Nested class declaration
- Nested interface declaration

You cannot include Java annotations directly in SQLJ programs, but you can include annotations in Java source code, and then include that source code in your SQLJ programs.

Example: Suppose that you declare the following marker annotation in a program called MyAnnot.java:

```
public @interface MyAnot { }
```

You also declare the following marker annotation in a program called MyAnnot2.java:

```
public @interface MyAnot2 { }
```

You can then use those annotations in an SQLJ program:

```
// Class annotations
@MyAnot2 public @MyAnot class  TestAnnotation
{
  // Field annotation
  @MyAnot
  private static final int field1 = 0;
  // Constructor annotation
  @MyAnot2 public @MyAnot TestAnnotation  () { }
   // Method annotation
   @MyAnot
   public static void main (String a[])
   {
      TestAnnotation TestAnnotation_o = new TestAnnotation();
      TestAnnotation_o.runThis();
   }
  // Inner class annotation
  public static @MyAnot class TestAnotherInnerClass { }
  // Inner interface annotation
  public static @MyAnot interface TestAnotInnerInterface { }
}
```

Enumerated types

An enumerated type is a data type that consists of a set of ordered values. The SDK for Java version 5 introduces the enum type for enumerated types.

You can include enums in the following places:

- In Java source files (.java files) that you include in an SQLJ program
- In SQLJ class declarations

Example: The TestEnum.sqlj class declaration includes an `enum` type:

```
public class TestEnum2
{
  public enum Color {
      RED,ORANGE,YELLOW,GREEN,BLUE,INDIGO,VIOLET}
  Color color;
  …                          // Get the value of color
  switch (color) {
    case RED:
    System.out.println("Red is at one end of the spectrum.");
    #sql[ctx] { INSERT INTO MYTABLE VALUES (:color) };
      break;
    case VIOLET:
    System.out.println("Violet is on the other end of the spectrum.");
      break;
    case ORANGE:
    case YELLOW:
    case GREEN:
  case BLUE:
  case INDIGO:
    System.out.println("Everything else is in the middle.");
      break;
}
```

Generics

You can use generics in your Java programs to assign a type to a Java collection. The SQLJ translator tolerates Java generic syntax. Although you can use generics in SQLJ host variables, the value of doing so is limited because the SQLJ translator cannot determine the types of those host variables.

Examples of generics that you can use in SQLJ programs are:

- A `List` of `List` objects:

```
List <List<String>> strList2 = new ArrayList<List<String>>();
```

- A `HashMap` in which the key/value pair has the `String` type:

```
Map <String,String> map = new HashMap<String,String>();
```

- A method that takes a `List` with elements of any type:

```
public void mthd(List <?> obj) {
…
}
```

Examples of invalid uses of generics in SQLJ programs are:

- Nested generics in the method return type:

```
public* List<Map<String, Object>> *method(String, String, String);
```

Enhanced `for` loop

The enhanced `for` lets you specify that a set of operations is performed on each member of a collection or array. You can use the iterator in the enhanced `for` loop in host expressions.

Example: INSERT each of the items in array names into table TAB.

```
String[] names = {"ABC","DEF","GHI"};
for (String n : names)
{
  #sql {INSERT INTO TAB (VARCHARCOL) VALUES(:n) };
}
```

Varargs

Varargs make it easier to pass an arbitrary number of values to a method. A Vararg in the last argument position of a method declaration indicates that the last arguments are an array or a sequence of arguments. An SQLJ program can use the passed arguments in host expressions.

Example: Pass an arbitrary number of parameters of type `Object`, to a method that inserts each parameter value into table TAB.

```
public void runThis(Object...  objects) throws SQLException
{
  for (Object obj : objects)
  {
    #sql { INSERT INTO TAB (VARCHARCOL) VALUES(:obj) };
  }
}
```

Transaction control in SQLJ applications

In SQLJ applications, as in other types of SQL applications, transaction control involves explicitly or implicitly committing and rolling back transactions, and setting the isolation level for transactions.

Setting the isolation level for an SQLJ transaction

To set the isolation level for a unit of work within an SQLJ program, use the SET TRANSACTION ISOLATION LEVEL clause.

About this task

The following table shows the values that you can specify in the SET TRANSACTION ISOLATION LEVEL clause and their data server equivalents.

Table 28. Equivalent SQLJ and data server isolation levels

SET TRANSACTION value	Data server isolation level
SERIALIZABLE	Repeatable read
REPEATABLE READ	Read stability
READ COMMITTED	Cursor stability
READ UNCOMMITTED	Uncommitted read

The isolation level affects the underlying JDBC connection as well as the SQLJ connection.

Related concepts

"JDBC connection objects" on page 23
When you connect to a data source by either connection method, you create a `Connection` object, which represents the connection to the data source.

Committing or rolling back SQLJ transactions

If you disable autocommit for an SQLJ connection, you need to perform explicit commit or rollback operations. You do this using execution clauses that contain the SQL COMMIT or ROLLBACK statements.

Example

To commit a transaction in an SQLJ program, use a statement like this:

```
#sql [myConnCtx] {COMMIT};
```

To roll back a transaction in an SQLJ program, use a statement like this:

```
#sql [myConnCtx] {ROLLBACK};
```

Related tasks

"Connecting to a data source using SQLJ" on page 121
In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

"Committing or rolling back SQLJ transactions" on page 171
If you disable autocommit for an SQLJ connection, you need to perform explicit commit or rollback operations. You do this using execution clauses that contain the SQL COMMIT or ROLLBACK statements.

Handling SQL errors and warnings in SQLJ applications

SQLJ clauses throw SQLExceptions when SQL errors occur, but not when most SQL warnings occur.

About this task

SQLJ generates an `SQLException` under the following circumstances:

- When any SQL statement returns a negative SQL error code
- When a SELECT INTO SQL statement returns a +100 SQL error code

You need to explicitly check for other SQL warnings.

Procedure

- For SQL error handling, include try/catch blocks around SQLJ statements.
- For SQL warning handling, invoke the `getWarnings` method after every SQLJ statement.

Handling SQL errors in an SQLJ application

SQLJ clauses use the JDBC class `java.sql.SQLException` for error handling.

Procedure

To handle SQL errors in SQLJ applications, following these steps:

1. Import the `java.sql.SQLException` class.
2. Use the Java error handling `try/catch` blocks to modify program flow when an SQL error occurs.
3. Obtain error information from the `SQLException`.

   You can use the `getErrorCode` method to retrieve SQL error codes and the `getSQLState` method to retrieve SQLSTATEs.

   If you are using the IBM Data Server Driver for JDBC and SQLJ, obtain additional information from the `SQLException` by casting it to a `DB2Diagnosable` object, in the same way that you obtain this information in a JDBC application.

Example

The following code prints out the SQL error that occurred if a SELECT statement fails.

```
try {
  #sql [ctxt] {SELECT LASTNAME INTO :empname
    FROM EMPLOYEE WHERE EMPNO='000010'};
}
catch(SQLException e) {
  System.out.println("Error code returned: " + e.getErrorCode());
}
```

Related tasks

"Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ" on page 111

As in all Java programs, error handling for JDBC applications is done using `try/catch` blocks. Methods throw exceptions when an error occurs, and the code in the `catch` block handles those exceptions.

Handling SQL warnings in an SQLJ application

Other than a +100 SQL error code on a SELECT INTO statement, warnings from the data server do not throw SQLExceptions. To handle warnings from the data server, you need to give the program access to the `java.sql.SQLWarning` class.

About this task

If you want to retrieve data-server-specific information about a warning, you also need to give the program access to the `com.ibm.db2.jcc.DB2Diagnosable` interface and the `com.ibm.db2.jcc.DB2Sqlca` class.

Procedure

To retrieve data-server-specific information about a warning:

1. Set up an execution context for that SQL clause. See "Control the execution of SQL statements in SQLJ" for information on how to set up an execution context.
2. To check for a warning from the data server, invoke the `getWarnings` method after you execute an SQLJ clause.

   `getWarnings` returns the first `SQLWarning` object that an SQL statement generates. Subsequent `SQLWarning` objects are chained to the first one.
3. To retrieve data-server-specific information from the `SQLWarning` object with the IBM Data Server Driver for JDBC and SQLJ, follow the instructions in "Handle an SQLException under the IBM Data Server Driver for JDBC and SQLJ".

Example

The following example demonstrates how to retrieve an `SQLWarning` object for an SQL clause with execution context execCtx. The numbers to the right of selected statements correspond to the previously-described steps.

```
ExecutionContext execCtx=myConnCtx.getExecutionContext();    1
                                    // Get default execution context from
                                    // connection context
SQLWarning sqlWarn;
…
#sql [myConnCtx,execCtx] {SELECT LASTNAME INTO :empname
  FROM EMPLOYEE WHERE EMPNO='000010'};
if ((sqlWarn = execCtx.getWarnings()) != null)              2
System.out.println("SQLWarning " + sqlWarn);
```

Related tasks

“Handling SQL errors in an SQLJ application” on page 172
SQLJ clauses use the JDBC class `java.sql.SQLException` for error handling.

Closing the connection to a data source in an SQLJ application

When you have finished with a connection to a data source, you need to close the connection to the data source. Doing so releases the data server resources and SQLJ resources for the associated `ConnectionContext` object immediately.

About this task

If you do not close a `ConnectionContext` object after you use it, unexpected behavior might occur if a Java finalizer closes the `ConnectionContext` object. Examples of the unexpected behavior are:

- An `ObjectClosedException` on the underlying `ResultSet` or `Statement` objects

- Agent hangs in Db2 stored procedures

Procedure

To close the connection to the data source, use one of the `ConnectionContext.close` methods.

- If you execute `ConnectionContext.close()` or `ConnectionContext.close(ConnectionContext.CLOSE_CONNECTION)`, the connection context, as well as the connection to the data source, are closed.
- If you execute `ConnectionContext.close(ConnectionContext.KEEP_CONNECTION)` the connection context is closed, but the connection to the data source is not.

Example

The following code closes the connection context, but does not close the connection to the data source.

```
…
ctx = new EzSqljctx(con0);          // Create a connection context object
                                    // from JDBC connection con0
…                                   // Perform various SQL operations
 EzSqljctx.close(ConnectionContext.KEEP_CONNECTION);
                                    // Close the connection context but keep
                                    // the connection to the data source open
```

Related tasks

“Connecting to a data source using SQLJ” on page 121
In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

Chapter 5. Java reactive applications for Db2 data servers

You can run Java applications against Db2 data servers by using the IBM Db2 Java Reactive Driver.

Creating Java reactive applications that utilize the Project Reactor framework requires a driver that provides a non-blocking, asynchronous API to access a data server. The IBM Db2 Java Reactive Driver, which uses Reactive Relational Database Connectivity (R2DBC), provides that capability. The IBM Db2 Java Reactive Driver can access data on the following data servers:

- Db2 data servers on Linux, UNIX, and Windows systems
- Db2 for z/OS data servers

The IBM Db2 Java Reactive Driver uses some third-party components. The following figure shows the relationship among the driver components and the third-party components.



Figure 46. IBM Db2 Java Reactive Driver architecture

For more details on the IBM Db2 Java Reactive Driver, see Java Reactive Driver.

The basic steps in creating a Java reactive application are:

1. Create a connection configuration:

```
DB2ConnectionConfiguration config = DB2ConnectionConfiguration.builder()
                .database("database-name")
```

© Copyright IBM Corp. 1998, 2017

```
                .host("host-name")
                .port(port-number)
                .username("username")
                .password("password")
                .conPoolSize(integer)
                .stmtCacheSize(integer)
                .build();
```

The `database`, `host`, `port`, `username`, and `password` parameter values provide the information for connecting to the target data server.

The `conPoolSize` value represents the maximum number of data server connections in the pool. The default value is 10.

The `stmtCacheSize` value represents the maximum number of statements to be cached in a connection. The default value is 30.

The API that is accessed by the IBM Db2 Java Reactive Driver uses a `DB2ConnectionFactory` object. That object, when instantiated, allows you to create a connection to a data server by calling the `create` method.

2. Using the connection `config` file, create your connection factory:

```
DB2ConnectionFactory factory = new DB2ConnectionFactory(config);
```

3. Using the `ConnectionFactory` object that you defined in the previous step, create a connection pool:

```
DB2ConnectionPool pool = new DB2ConnectionPool(factory);
```

4. Obtain a connection from the connection pool. You can now run DDL statements asynchronously against the Db2 data server from your Java reactive application.

The following example shows the command syntax and output from obtaining a connection from a connection pool and running a DDL statement to create a DEMO table:

```
AtomicReference<DB2Connection> con = new AtomicReference<DB2Connection>();

    Mono<Void> mono = pool.getConnection()
            .doOnNext(c -> con.set(c))
            .flatMap(c -> c.executeUpdate(
                    "CREATE TABLE DEMO (" +
                        "ID INTEGER UNIQUE NOT NULL, " +
                        "ACC_BAL DECIMAL(10,2) NOT NULL, " +
                        "AS_OF TIMESTAMP NOT NULL" +
                    ")"
            ))
            .doOnTerminate(() -> con.get().release());
```

The following example shows a DML statement for adding data into the newly created table, DEMO:

```
    Mono<DB2Result> mono = pool.getConnection()
        .doOnNext(c -> con.set(c))
        .flatMap(c -> c.createStatement("INSERT INTO DEMO (ID, ACC_BAL,
                     AS_OF) VALUES (?, ?, ?)")
                           .bind(1, id)
                           .bind(2, amount)
                           .bind(3, Timestamp.from(Instant.now()))
                           .execute())
        .doAfterTerminate(() -> con.get().release());
```

The following example shows the command syntax for closing connections in a connection pool:

```
// Close all the connections in the pool
Mono<Void> mono = pool.closeAll();
```

Related information

Java Reactive Driver

Chapter 6. Java stored procedures and user-defined functions

Like stored procedures and user-defined functions in any other language, Java stored procedures and user-defined functions are programs that can contain SQL statements. You invoke Java stored procedures from a client program that is written in any supported language.

The following topics contain information that is specific to defining and writing Java user-defined functions and stored procedures.

In these topics, the word *routine* refers to either a stored procedure or a user-defined function.

Related information

Db2 for z/OS Stored Procedures: Through the CALL and Beyond (IBM Redbooks)

Setting up the environment for Java routines

Before you can run Java routines, you need to set up a WLM environment and set Java environment variables.

Before you begin

Before you can prepare and run Java routines, you need to satisfy the following prerequisites:

- Java 2 Technology Edition, V5 or later.

  The IBM Data Server Driver for JDBC and SQLJ supports 31-bit or 64-bit Java routines. For 64-bit Java routines, you need Java 2 Technology Edition, V6 or later.
- TCP/IP

  TCP/IP is required on the client and all database servers to which you connect.
- The 4.*xx* version of the IBM Data Server Driver for JDBC and SQLJ that matches the Db2 for z/OS version.

  If you are migrating from a previous release of Db2 for z/OS, you need to install the corresponding version of the IBM Data Server Driver for JDBC and SQLJ.

About this task

The steps in this task are necessary for preparing and running Java routines.

If you plan to use IBM Optim Development Studio to prepare and run your Java routines, see Developing Db2 for z/OS stored procedures (IBM Data Studio)

Procedure

To set up the environment for running Java routines, you need to perform these tasks:

1. Ensure that your operating system, SDK for Java, and the IBM Data Server Driver for JDBC and SQLJ are at the correct levels, and that you have installed all prerequisite products.

   Important: If you have migrated the Db2 subsystem from a previous release of Db2 for z/OS, your existing Java stored procedures and user-defined function no longer work with the previous release of the IBM Data Server Driver for JDBC and SQLJ and the current release of Db2 for z/OS. You need to install the version of the IBM Data Server Driver for JDBC and SQLJ that matches the Db2 for z/OS release level, and update the WLM-managed stored procedure address space configuration and JAVAENV data set to use the current driver.
2. Create the Workload Manager for z/OS (WLM) application environment for running the routines.
3. Set up the run-time environment for Java routines, which includes setting environment variables.

© Copyright IBM Corp. 1998, 2017

Setting up the WLM application environment for Java routines

You need different WLM application environments for Java routines from the WLM application environments that you use for other routines.

About this task

Setting up a WLM environment for Java routines involves the same basic steps as setting up a WLM environment for other routines.

Procedure

1. Create a WLM environment startup procedure for Java routines.
2. Define the WLM environment to WLM.

WLM address space startup procedure for Java routines

The WLM address space startup procedure for Java routines requires extra DD statements that other routines do not need.

The following figure shows an example of a startup procedure for an address space in which Java routines can run. The JAVAENV DD statement indicates to Db2 that the WLM environment is for Java routines.

```
//DSNWLM PROC RGN=0K,APPLENV=WLMIJAV,DB2SSN=DSN,NUMTCB=5,  1
//       MNSPAS=0

//IEFPROC EXEC PGM=DSNX9WLM,REGION=&RGN,TIME=NOLIMIT,
// PARM='&DB2SSN,&NUMTCB,&APPLENV,&MNSPAS'                 2
//STEPLIB DD DISP=SHR,DSN=DSNC10.RUNLIB.LOAD
// DD DISP=SHR,DSN=CEE.SCEERUN
// DD DISP=SHR,DSN=DSNC10.SDSNEXIT
// DD DISP=SHR,DSN=DSNC10.SDSNLOAD
// DD DISP=SHR,DSN=DSNC10.SDSNLOD2
//JAVAENV DD DISP=SHR,DSN=WLMIJAV.JSPENV                   3
//JSPDEBUG DD SYSOUT=A                                     4
//CEEDUMP DD SYSOUT=A
//SYSPRINT DD SYSOUT=A
```

Figure 47. Startup procedure for a WLM address space in which a Java routine runs

Notes to Figure 47 on page 178:

Note	Explanation
1	In this statement: • Change the DB2SSN value to your Db2 for z/OS subsystem name. • Change the APPLENV value to the name of the application environment that you set up for Java stored procedures. • If your stored procedure address space runs routines in 31-bit Java virtual machines (JVMs), the recommended NUMTCB value is 5. For testing a Java stored procedure, NUMTCB=1 is recommended. With NUMTCB=1, only one JVM is started, so refreshing the WLM environment after you change the stored procedure takes less time. If your stored procedure address space runs routines in a 64-bit, multi-threaded environment, the recommended NUMTCB value is 25. The NUMTCB value specifies the number of concurrent stored procedure executions within the single JVM that runs in the stored procedure address space. • Change the MNSPAS value to the minimum number of stored procedure address spaces that WLM starts and maintains. Valid values are 0 to 50. If you specify 0, WLM starts and shuts down stored procedure address spaces as applications require them. Specify a value of greater than 0 if the overhead of starting and shutting down stored procedure address spaces and JVMs makes your response time unacceptable.

Note	Explanation
2	DSNX9WLM is the program that is executed to run stored procedures in a 31-bit stored procedure environment. To run Java routines in a 64-bit, multi-threaded environment, change DSNX9WLM to DSNX9WJM.
3	JAVAENV specifies a data set that contains Language Environment® run-time options for Java stored procedures. The presence of this DD statement indicates to Db2 that the WLM environment is for Java routines. This data set must contain the environment variable JAVA_HOME. This environment variable indicates to Db2 that the WLM environment is for Java routines. JAVA_HOME also specifies the highest-level directory in the set of directories that contain the SDK for Java.
4	Specifies a data set into which Db2 puts information that you can use to debug your stored procedure. The information that Db2 collects is for assistance in debugging setup problems, and should be used only under the direction of IBM Software Support. You should comment out this DD statement during production.

Related concepts

“WLM application environment values for Java routines” on page 179
To define the application environment for Java routines to WLM, specify the appropriate values on WLM setup panels.

“Runtime environment for Java routines” on page 180
For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

WLM application environment values for Java routines

To define the application environment for Java routines to WLM, specify the appropriate values on WLM setup panels.

Use values like those that are shown in the following screen examples.

```
  File  Utilities  Notes  Options  Help
------------------------------------------------------------------------
                    Definition Menu     WLM Appl
Command ===> ____________________________________________________________

Definition data set . :  none
Definition name  . . . . WLMENV
Description . . . . . .  Environment for Java stored procedures
Select one of the
following options. . .   9  1. Policies
                           2. Workloads
                           3. Resource Groups
                           4. Service Classes
                           5. Classification Groups
                           6. Classification Rules
                           7. Report Classes
                           8. Service Coefficients/Options
                           9. Application Environments
                          10. Scheduling Environments
```

Definition name
Specify the name of the WLM application environment that you are setting up for stored procedures.

Description
Specify any value.

Options
Specify 9 (Application Environments).

```
  Application-Environment  Notes  Options  Help
------------------------------------------------------------------------------
                     Create an Application Environment
Command ===> ____________________________________________________________

Application Environment Name . : WLMENV
Description  . . . . . . . . . . Environment for Java stored procedures
Subsystem Type . . . . . . . . . DB2
Procedure Name . . . . . . . . . DSN8WLMP
Start Parameters . . . . . . . . DB2SSN=DB2T,NUMTCB=3,APPLENV=WLMENV
                                 ---------------------------------------
                                 -----------------------------------

Limit on starting server address spaces for a subsystem instance:
1   1.  No limit.
    2.  Single address space per system.
    3.  Single address spaces per sysplex.
```

Subsystem Type
Specify Db2.

Procedure Name
Specify a name that matches the name of the JCL startup procedure for the stored procedure address spaces that are associated with this application environment.

Start Parameters
If the Db2 subsystem in which the stored procedure runs is not in a sysplex, specify a DB2SSN value that matches the name of that Db2 subsystem. If the same JCL is used for multiple Db2 subsystems, specify DB2SSN=&IWMSSNM. The NUMTCB value depends on the type of stored procedure you are running. For Java routines that run in a 31-bit environment, the recommended value is 5. For Java routines that run in a 64-bit environment, the recommended value is 25. Specify an APPLENV value that matches the value that you specify on the CREATE PROCEDURE or CREATE FUNCTION statement for the routines that run in this application environment.

Limit on starting server address spaces for a subsystem instance
Specify 1 (no limit).

Related concepts

“WLM address space startup procedure for Java routines” on page 178
The WLM address space startup procedure for Java routines requires extra DD statements that other routines do not need.

“Runtime environment for Java routines” on page 180
For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

Runtime environment for Java routines

For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

Create the data set for the runtime options with the characteristics that are listed in the following table.

Option	Value
Primary space allocation	1 block
Secondary space allocation	1 block
Record format	VB
Record length	255
Block size	4096

After you create the data set, edit it to insert a Language Environment options string, which has this form:



The maximum length of the Language Environment runtime options string in a JAVAENV data set for Java stored procedures is 245 bytes. If you exceed the maximum length, Db2 truncates the contents but does not issue a message. If you enter the contents of the JAVAENV data set on more than one line, Db2 concatenates the lines to form the runtime options string. The runtime options string can contain no leading or trailing blanks. Within the string, only blanks that are valid within an option are permitted.

If your environment variable list is long enough that the JAVAENV content is greater than 245 bytes, you can put the environment variable list in a separate data set in a separate file, and use the environment variable _CEE_ENVFILE to point to that file.

The descriptions of the parameters are:

_CEE_ENVFILE
Specifies a z/OS UNIX System Services data set that contains some or all of the settings for environment variables.

Use the _CEE_ENVFILE parameter if the length of environment variable string causes the total length of the JAVAENV content to exceed 245 bytes, which is the Db2 limit for the JAVAENV content.

The data set must be variable-length.The format for environment variable settings in this data set is:

```
environment-variable-1=setting-1
environment-variable-2=setting-2
…
environment-variable-n=setting-n
```

You can specify some of your environment variable settings as arguments of ENVAR and put some of the settings in this data set, or you can put all of your environment variable settings in this data set.

For example, to use file /u/db2c10/javasp/jspnolimit.txt for environment variable settings, specify:

```
_CEE_ENVFILE=/u/db2c10/javasp/jspnolimit.txt
```

ENVAR
Sets the initial values for specified environment variables. The environment variables that you might need to specify are:

CLASSPATH
When you prepare your Java routines, if you do not put your routine classes into JAR files, include the directories that contain those classes. For example:

```
CLASSPATH=.:/U/DB2RES3/ACMEJOS
```

Do not include directories for JAR files for JDBC or the JDK in the CLASSPATH. If you use a DB2JccConfiguration.properties file, you need to include the directory that contains that file in the CLASSPATH.

DB2_BASE
The value of DB2_BASE is the highest-level directory in the set of HFS directories that contain Db2 for z/OS code.

For example:

```
DB2_BASE=/usr/lpp/db2c10/base
```

The default is /usr/lpp/db2c10/base.

JAVA_HOME
This environment variable indicates to Db2 that the WLM environment is for Java routines. The value of JAVA_HOME is the highest-level directory in the set of directories that contain the SDK for Java. For example:

```
JAVA_HOME=/usr/lpp/java/IBM/J6.0
```

JCC_HOME
The value of JCC_HOME is the highest-level directory in the set of directories that contain the JDBC driver. For example:

```
JCC_HOME=/usr/lpp/db2c10/jdbc
```

JCC_HOME must be set.

JDBCSTD
Specifies which version of the IBM Data Server Driver for JDBC and SQLJ that Java routines use. Possible values are:

3
Java routines use the version of the driver that supports JDBC 3.0.

4
Java routines use the version of the driver that supports JDBC 4.0.

To run multiple Java stored procedures concurrently in a 64-bit JVM, you must set JDBCSTD to 4.

JVM_DEBUG_PORTRANGE
This environment variable specifies a range of ports that the JVM listens on for debug connections, in the form *low-port-number*::*high-port-number*. The default is ports 8000 to 8050. For example:

```
JVM_DEBUG_PORTRANGE=8051::8055
```

Specify JVM_DEBUG_PORTRANGE only for WLM environments that are used for debugging Java routines.

JVMPROPS
This environment variable specifies the name of a z/OS UNIX System Services file that contains startup options for the JVM in which the stored procedure runs. For example:

```
JVMPROPS=/usr/lpp/java/properties/jvmsp
```

The following example shows the contents of a startup options file that you might use for a JVM in which Java stored procedures run:

```
# Properties file for JVM for Java stored procedures
# Sets the initial size of middleware heap within non-system heap
-Xms64M

# Sets the maximum size of nonsystem heap
-Xmx128M

#initial size of system heap
-Xinitsh512K
```

For information about JVM startup options, see *IBM 31-bit and 64-bit SDKs for z/OS, Java 2 Technology Edition, Version 5 SDK and Runtime Environment User Guide*, available at:

```
http://www.ibm.com/servers/eserver/zseries/software/java
```

Click the Reference Information link.

LC_ALL
Modify LC_ALL to change the locale to use for the locale categories when the individual locale environment variables specify locale information. This value needs to match the CCSID for the Db2 subsystem on which the stored procedures run. For example:

```
LC_ALL=En_US.IBM-037
```

TZ
Modify TZ to change the local timezone. For example:

```
TZ=PST08
```

The default is GMT (UTC).

USE_LIBJVM_G
Specifies whether the debug version of the JVM is used instead of the default, non-debug version of the JVM. The debug version of the JVM is in dynamic link library libjvm_g. If USE_LIBJVM_G is not specified, or its value is anything other than the capitalized string YES, the non-debug version of the JVM is used. For example, USE_LIBJVM_G=NO causes the non-debug version of the JVM to be used.

If USE_LIBJVM_G=YES, the JVMPROPS environment variable must specify a file that contains JVM startup options. That file must contain the startup option -Djava.execsuffix=_g.

Specify USE_LIBJVM_G=YES only under the direction of IBM Software Support.

WORK_DIR
Modify WORK_DIR to change the default destination for STDOUT and STDERR output.

MSGFILE
Specifies the DD name of a data set in which Language Environment puts runtime diagnostics. All subparameters in the MSGFILE parameter are optional. The default is

```
MSGFILE(SYSOUT,FBA,121,0,NOENQ)
```

If you specify a data set name in the JSPDEBUG statement of your stored procedure address space startup procedure, you need to specify JSPDEBUG as the first parameter. If the NUMTCB value in the stored procedure address space startup procedure is greater than 1, you need to specify ENQ as the fifth subparameter. Language Environment run-time options (z/OS Language Environment Customization) contains complete information about MSGFILE.

Do not specify the MSGFILE parameter in a 64-bit environment.

STACK or STACK64
Controls the allocation of the stack storage of a thread. Specify STACK in a 31-bit environment. Specify STACK64 in a 64-bit environment.

XPLINK(ON)
Causes the initialization of the XPLINK environment. This option must be specified for a 31-bit environment, and should not be specified for a 64-bit environment.

The following example shows the contents of a JAVAENV data set.

```
ENVAR("JCC_HOME=/usr/lpp/db2c10/jdbc",
"JAVA_HOME=/usr/lpp/java160/J6.0",
"WORK_DIR=/u/db2c10/tmp"),
MSGFILE(JSPDEBUG,,,,ENQ)
```

For information on environment variables that are related to locales, see *z/OS C/C++ Programming Guide*.

Related concepts

“WLM address space startup procedure for Java routines” on page 178
The WLM address space startup procedure for Java routines requires extra DD statements that other routines do not need.

“WLM application environment values for Java routines” on page 179

To define the application environment for Java routines to WLM, specify the appropriate values on WLM setup panels.

Moving from 31-bit Java routines to 64-bit Java routines

Modify your existing 31-bit Java routine environments to run Java routines in a 64-bit Java virtual machine (JVM). This change can provide better scalability and performance.

About this task

A stored procedure address space in which JVMs use 64-bit addressing supports a multi-threaded JVM model. With this model, the WLM address space starts a single JVM that can concurrently execute multiple Java stored procedures or user-defined functions. This model is more efficient than the 31-bit model, in which a single routine runs in a JVM.

To run Java routines in 64-bit JVMs, you need to make several changes to the environment and to your Java applications.

Procedure

1. Define a startup procedure for a WLM environment in which 64-bit JVMs can run.

   The following JCL shows an example of such a WLM startup procedure.

```
//DSNWJ64 PROC RGN=0K,APPLENV=DSNWLM_JAVA64,DB2SSN=DSN,     1
//       NUMTCB=25,MNSPAS=0
//IEFPROC EXEC PGM=DSNX9WJM,REGION=&RGN,TIME=NOLIMIT,       2
// PARM='&DB2SSN,&NUMTCB,&APPLENV,&MNSPAS'

//STEPLIB DD DISP=SHR,DSN=DSNC10.RUNLIB.LOAD
// DD DISP=SHR,DSN=CEE.SCEERUN
// DD DISP=SHR,DSN=DSNC10.SDSNEXIT
// DD DISP=SHR,DSN=DSNC10.SDSNLOAD
// DD DISP=SHR,DSN=DSNC10.SDSNLOD2
//JAVAENV DD DISP=SHR,DSN=WLMIJAV.JSPENV
//JSPDEBUG DD SYSOUT=A
//CEEDUMP DD SYSOUT=A
//SYSPRINT DD SYSOUT=A
```

Note	Explanation
1	In a 64-bit environment, NUMTCB controls the number of concurrent Java stored procedure executions in a JVM. NUMTCB can be higher for a WLM address space that supports 64-bit JVMs than for one that supports 31-bit JVMs.
2	Program DSNX9WJM supports 64-bit JVMs.

2. Alter your stored procedure or user-defined function definitions to specify a WLM environment name that matches the APPLENV value in the previous step.
3. Define the application environment for 64-bit Java routines to WLM.

   In WLM setup panels, use values like those that are shown in the following screen examples.

```
  File  Utilities  Notes  Options  Help
------------------------------------------------------------------------
                      Definition Menu     WLM Appl
Command ===> ____________________________________________________________

Definition data set . :  none
Definition name  . . . . DSNWLM_JAVA64
Description . . . . . .  Environment for Java stored procedures
Select one of the
following options. . .   9  1. Policies
                           2. Workloads
                           3. Resource Groups
                           4. Service Classes
                           5. Classification Groups
                           6. Classification Rules
                           7. Report Classes
                           8. Service Coefficients/Options
                           9. Application Environments
                          10. Scheduling Environments
```

Definition name
Specify the name of the WLM application environment that you are setting up for 64-bit routines. This is the same application environment name that you specified in the ALTER PROCEDURE or ALTER FUNCTION statement in the previous step.

Description
Specify any value.

Options
Specify 9 (Application Environments).

```
  Application-Environment  Notes  Options  Help
------------------------------------------------------------------------
                      Create an Application Environment
Command ===> ____________________________________________________________

Application Environment Name . : DSNWLM_JAVA64
Description  . . . . . . . . . . Environment for 64-bit Java routines
Subsystem Type . . . . . . . . . DB2
Procedure Name . . . . . . . . . DSNWJ64
Start Parameters . . . . . . . . DB2SSN=DB2T,NUMTCB=25,APPLENV=DSNWLM_JAVA64
                                 ______________________________________
                                 ______________________________________

Limit on starting server address spaces for a subsystem instance:
1   1.  No limit.
    2.  Single address space per system.
    3.  Single address spaces per sysplex.
```

Subsystem Type
Specify Db2.

Procedure Name
Specify a name that matches the name of the JCL startup procedure for the stored procedure address spaces that are associated with this application environment.

Start Parameters
If the Db2 subsystem in which the stored procedure runs is not in a sysplex, specify a DB2SSN value that matches the name of that Db2 subsystem. If the same JCL is used for multiple Db2 subsystems, specify DB2SSN=&IWMSSNM. The NUMTCB value depends on the type of stored procedure you are running. For running 64-bit Java routines, the recommended value is 25. Specify an APPLENV value that matches the value that you that you specified in the ALTER PROCEDURE or ALTER FUNCTION statement in the previous step.

Limit on starting server address spaces for a subsystem instance
Specify 1 (no limit).

4. For Java routines that make Java Native Interface calls, recompile and link-edit the DLLs for the native functions in 64-bit mode.
5. This step is necessary only for a Java routine that is in a JAR file that is installed in the Db2 catalog, when the routine definition specifies a COLLID value that is not NULLID.

If the Java routine definition specifies a COLLID value that is different from the collection into which the IBM Data Server Driver for JDBC and SQLJ packages are bound, run the DB2Binder utility with the -collection option to bind the driver packages into the same collection as the Java routine COLLID value. If you do not do so, you might receive SQLCODE -805 when a Java routine executes in a 64-bit environment.

Related information

-805 (Db2 Codes)

Defining Java routines and JAR files to Db2

Before you can use a Java routine, you need to define it to Db2.

About this task

Use the following procedure to manually define a Java routine to Db2. If you use IBM Optim Development Studio, IBM Optim Development Studio creates the definitions.

Procedure

1. Execute the CREATE PROCEDURE or CREATE FUNCTION statement to define the routine to Db2. To alter the routine definition, use the ALTER PROCEDURE or ALTER FUNCTION statement.
2. Optional: If the routines are in JAR files, define the JAR files to Db2.

   If the routines are in JAR files, it is recommended that you also define the JAR files to Db2. Alternatively, you can include the JAR file name in the CLASSPATH.

   To define the JAR files to Db2:

   - Use the SQLJ.INSTALL_JAR or SQLJ.DB2_INSTALL_JAR built-in stored procedure to define the JAR files to Db2.
   - After you have installed a JAR, if that JAR references classes in other installed JARs, use the SQLJ.ALTER_JAVA_PATH stored procedure to specify the class resolution path that the JVM searches to resolve those class references.
   - To replace the JAR file, use the SQLJ.REPLACE_JAR or SQLJ.DB2_REPLACE_JAR stored procedure.
   - To remove the JAR file, use the SQLJ.REMOVE_JAR or SQLJ.DB2_REMOVE_JAR stored procedure.

   SQLJ.INSTALL_JAR, SQLJ, SQLJ.REPLACE_JAR, and SQLJ.REMOVE_JAR can be used only with the local Db2 catalog. The other stored procedures can be used with remote or local Db2 catalogs.

Definition of a Java routine to Db2

Before you can use a Java routine, you need to define it to Db2 using the CREATE PROCEDURE or CREATE FUNCTION statement.

The definition for a Java routine is much like the definition for a routine in any other language. However, the following parameters have different meanings for Java routines.

LANGUAGE

Specifies the application programming language in which the routine is written.

Specify LANGUAGE JAVA.

You cannot specify LANGUAGE JAVA for a user-defined table function.

EXTERNAL NAME

Specifies the program that runs when the procedure name is specified in a CALL statement or the user-defined function name is specified in an SQL statement. For Java routines, the argument of EXTERNAL NAME is a string that is enclosed in single quotation marks. The EXTERNAL NAME clause for a Java routine has the following syntax:



Notes:

[1] For compatibility with Db2, you can use an exclamation point (!) after *JAR-name* instead of a colon.

[2] For compatibility with previous versions of Db2, you can use a slash (/) after *package-name* instead of a period.

Whether you include *JAR-name* depends on where the Java code for the routine resides. If you create a JAR file from the class file for the routine (the output from the javac command), you need to include *JAR-name*. You must create the JAR file and define the JAR file to Db2 before you execute the CREATE PROCEDURE or CREATE FUNCTION statement. If some other user executes the CREATE PROCEDURE or CREATE FUNCTION statement, you need to grant the USAGE privilege on the JAR to them.

If you use a JAR file, that JAR file must refer to classes that are contained in that JAR file, are found in the CLASSPATH, or are system-supplied. Classes that are in directories that are referenced in DB2_HOME or JCC_HOME, and JAVA_HOME do not need to be included in the JAR file.

Whether you include *(method-signature)* depends on the following factors:

- The way that you define the parameters in your routine method

  Each SQL data type has a corresponding default Java data type. If your routine method uses data types other than the default types, you need to include a method signature in the EXTERNAL NAME clause. A method signature is a comma-separated list of data types.
- Whether you overload a Java routine

  If you have several Java methods in the same class, with the same name and different parameter types, you need to specify the method signature to indicate which version of the program is associated with the Java routine.

If your stored procedure returns result sets, you also need to include a parameter in the method signature for each result set. The parameter can be in one of the following forms:

- `java.sql.ResultSet[]`
- An array of an SQLJ iterator class

You do *not* include these parameters in the parameter list of the SQL CALL statement when you invoke the stored procedure.

Example: EXTERNAL NAME clause for a Java user-defined function: Suppose that you write a Java user-defined function as method getSals in class S1Sal and package s1. You put S1Sal in a JAR file named sal_JAR and install that JAR in Db2. The EXTERNAL NAME parameter is :

```
EXTERNAL NAME 'sal_JAR:s1.S1Sal.getSals'
```

Example: EXTERNAL NAME clause for a Java stored procedure: Suppose that you write a Java stored procedure as method getSals in class S1Sal. You put S1Sal in a JAR file named sal_JAR and install that JAR in Db2. The stored procedure has one input parameter of type INTEGER and returns one result set. The Java method for the stored procedure receives one parameter of type java.lang.Integer, but the default Java data type for an SQL type of INTEGER is int, so the EXTERNAL NAME clause requires a signature clause. The EXTERNAL NAME parameter is :

```
EXTERNAL NAME 'sal_JAR:S1Sal.getSals(java.lang.Integer,java.sql.ResultSet[])'
```

NO SQL

Indicates that the routine does not contain any SQL statements.

For a Java routine that is stored in a JAR file, you cannot specify NO SQL.

PARAMETER STYLE
Identifies the linkage convention that is used to pass parameters to the routine.

For a Java routine, the only value that is valid is PARAMETER STYLE JAVA.

You cannot specify PARAMETER STYLE JAVA for a user-defined table function.

WLM ENVIRONMENT
Identifies the MVS workload manager (WLM) environment in which the routine is to run.

If you do not specify this parameter, the routine runs in the default WLM environment that was specified when Db2 was installed.

PROGRAM TYPE
Specifies whether Language Environment runs the routine as a main routine or a subroutine.

This parameter value must be PROGRAM TYPE SUB.

RUN OPTIONS
Specifies the Language Environment run-time options to be used for the routine.

This parameter has no meaning for a Java routine. If you specify this parameter with LANGUAGE JAVA, Db2 issues an error.

SCRATCHPAD
Specifies that when the user-defined function is invoked for the first time, Db2 allocates memory for a scratchpad.

You cannot use a scratchpad in a Java user-defined function. Do not specify SCRATCHPAD when you create or alter a Java user-defined function.

FINAL CALL
Specifies that a final call is made to the user-defined function, which the function can use to free any system resources that it has acquired.

You cannot perform a final call when you call a Java user-defined function. Do not specify FINAL CALL when you create or alter a Java user-defined function.

DBINFO
Specifies that when the routine is invoked, an additional argument is passed that contains environment information.

You cannot pass the additional argument when you call a Java routine. Do not specify DBINFO when you call a Java routine.

SECURITY
Specifies how the routine interacts with an external security product, such as RACF, to control access to non-SQL resources. The values of the SECURITY parameter are the same for a Java routine as for any other routine. However, the value of the SECURITY parameter determines the authorization ID that must have authority to access z/OS UNIX System Services. The values of SECURITY and the IDs that must have access to z/OS UNIX System Services are:

Db2
The user ID that is defined for the stored procedure address space in the RACF started-procedure table.

EXTERNAL
The invoker of the routine.

DEFINER
The definer of the routine.

ALLOW DEBUG MODE, DISALLOW DEBUG MODE, or DISABLE DEBUG MODE
Specifies whether a Java stored procedure can be run in debugging mode. When DYNAMICRULES run behavior is in effect, the default is determined by using the value of the CURRENT DEBUG MODE special register. Otherwise the default is DISALLOW DEBUG MODE.

ALLOW DEBUG MODE
Specifies that the procedure can be run in debugging mode.

DISALLOW DEBUG MODE
Specifies that the procedure cannot be run in debugging mode.

You can use an ALTER PROCEDURE statement to change this option to ALLOW DEBUG MODE.

DISABLE DEBUG MODE
Specifies that the procedure can never be run in debugging mode.

The procedure cannot be changed to specify ALLOW DEBUG MODE or DISALLOW DEBUG MODE once the procedure has been created or altered using DISABLE DEBUG MODE. To change this option, you must drop and recreate the procedure using the desired option.

Example: Defining a Java stored procedure: Suppose that you have written and prepared a stored procedure that has these characteristics:

Clause	Description
Fully-qualified procedure name	SYSPROC.S1SAL
Parameters	DECIMAL(10,2) INOUT
Language	Java
Collection ID for the stored procedure package	DSNJDBC
Package, class, and method name	s1.S1Sal.getSals
Type of SQL statements in the program	Statements that modify Db2 tables
WLM environment name	WLMIJAV
Maximum number of result sets returned	1

This CREATE PROCEDURE statement defines the stored procedure to Db2:

```
CREATE PROCEDURE SYSPROC.S1SAL
 (DECIMAL(10,2) INOUT)
  FENCED
  MODIFIES SQL DATA
  COLLID DSNJDBC
  LANGUAGE JAVA
  EXTERNAL NAME  's1.S1Sal.getSals'
  WLM ENVIRONMENT WLMIJAV
  DYNAMIC RESULT SETS 1
  PROGRAM TYPE SUB
  PARAMETER STYLE JAVA;
```

Example: Defining a Java user-defined function: Suppose that you have written and prepared a user-defined function that has these characteristics:

Clause	Description
Fully-qualified function name	MYSCHEMA.S2SAL
Input parameter	INTEGER
Data type of returned value	VARCHAR(20)
Language	Java
Collection ID for the function package	DSNJDBC
Package, class, and method name	s2.S2Sal.getSals
Java data type of the method input parameter	java.lang.Integer
JAR file that contains the function class	sal_JAR

Clause	Description
Type of SQL statements in the program	Statements that modify Db2 tables
Function is called when input parameter is null?	Yes
WLM environment name	WLMIJAV

This CREATE FUNCTION statement defines the user-defined function to Db2:

```
CREATE FUNCTION MYSCHEMA.S2SAL(INTEGER)
  RETURNS VARCHAR(20)
  FENCED
  MODIFIES SQL DATA
  COLLID DSNJDBC
  LANGUAGE JAVA
  EXTERNAL NAME  'sal_JAR:s2.S2Sal.getSals(java.lang.Integer)'
  WLM ENVIRONMENT WLMIJAV
  CALLED ON NULL INPUT
  PROGRAM TYPE SUB
  PARAMETER STYLE JAVA;
```

In this function definition, you need to specify a method signature in the EXTERNAL NAME clause because the data type of the method input parameter is different from the default Java data type for an SQL type of INTEGER.

Related concepts

“Definition of a JAR file for a Java routine to Db2” on page 190
One way to organize the classes for a Java routine is to collect those classes into a JAR file. If you do this, you need to install the JAR file into the Db2 catalog.

Related reference

ALTER FUNCTION (external) (Db2 SQL)
ALTER PROCEDURE (external) (Db2 SQL)
CREATE FUNCTION (Db2 SQL)
CREATE PROCEDURE (external) (Db2 SQL)

Definition of a JAR file for a Java routine to Db2

One way to organize the classes for a Java routine is to collect those classes into a JAR file. If you do this, you need to install the JAR file into the Db2 catalog.

Db2 provides built-in stored procedures that perform the following functions for the JAR file:

SQLJ.INSTALL_JAR
Installs a JAR file into the local Db2 catalog.

SQLJ.DB2_INSTALL_JAR
Installs a JAR file into the local Db2 catalog or a remote Db2 catalog.

SQLJ.REPLACE_JAR
Replaces an existing JAR file in the local Db2 catalog.

SQLJ.DB2_REPLACE_JAR
Replaces an existing JAR file in the local Db2 catalog or a remote Db2 catalog.

SQLJ.REMOVE_JAR
Deletes a JAR file from the local Db2 catalog or a remote Db2 catalog.

SQLJ.ALTER_JAVA_PATH
Modifies the class resolution path of an previously installed JAR file to a specified value.

You can use IBM Optim Development Studio to install JAR files into the Db2 catalog, or you can write a client program that executes SQL CALL statements to invoke these stored procedures.

Related concepts

“Definition of a Java routine to Db2” on page 186

Before you can use a Java routine, you need to define it to Db2 using the CREATE PROCEDURE or CREATE FUNCTION statement.

Java routine programming

A *Java routine* is a Java application program that runs in a stored procedure address space. It can include JDBC methods or SQLJ clauses.

A Java routine is much like any other Java program and follows the same rules as routines in other languages. It receives input parameters, executes Java statements, optionally executes SQLJ clauses, JDBC methods, or a combination of both, and returns output parameters.

Differences between Java routines and stand-alone Java programs

Java routines differ in a few basic ways from stand-alone Java programs.

Those differences are:

- In a Java routine, a JDBC connection or an SQLJ connection context can use the connection to the data source that processes the CALL statement or the user-defined function invocation. The URL that identifies this default connection is jdbc:default:connection.
- The top-level method for a Java routine must be declared as static and public.

  Although you can use static and final variables in a Java routine without problems, you might encounter problems when you use static and non-final variables. You cannot guarantee that a static and non-final variable retains its value in the following circumstances:

  – Across multiple invocations of the same routine
  – Across invocations of different routines that reference that variable
- As in routines in other languages, the SQL statements that you can execute in the routine depend on whether you specify an SQL access level of CONTAINS SQL, READS SQL DATA, or MODIFIES SQL DATA.

Related concepts

“Differences between Java routines and other routines” on page 191
Java routines differ in a few basic ways from routines that are written in other programming languages.

Related reference

SQL statement data access classification for routines (Db2 SQL)

Differences between Java routines and other routines

Java routines differ in a few basic ways from routines that are written in other programming languages.

A Java routine differs from stored procedures that are written in other languages in the following ways:

- A Java routine must be defined with PARAMETER STYLE JAVA. PARAMETER STYLE JAVA specifies that the routine uses a parameter-passing convention that conforms to the Java language and SQLJ specifications. Db2 passes INOUT and OUT parameters as single-entry arrays. This means that in your Java routine, you must declare OUT or INOUT parameters as arrays. For example, suppose that stored procedure sp_one_out has one output parameter of type int. You declare the parameter like this:

  ```
  public static void routine_one_out (int[] out_parm)
  ```
- Java routines that are Java main methods have these restrictions:

  – The method must have a signature of String[]. It must be possible to map all the parameters to Java variables of type java.lang.String.
  – The routine can have only IN parameters.
- You cannot make instrumentation facility interface (IFI) calls in Java routines.
- You cannot specify an SQL access level of NO SQL for Java routines.
- As in other Java programs, you cannot include the following statements in a Java routine:

  - CONNECT
  - RELEASE
  - SET CONNECTION
- Routine parameters have different mappings to host language data types than the mappings of routine parameters to host language parameters for other languages.
- The technique for returning result sets from Java stored procedures is different from the technique for returning result sets in other stored procedures.
- When a Java routine executes, Java dynamically loads classes when new class references occur in the class that is being executed. During the class loading process, a `java.lang.ClassNotFoundException` or `java.lang.NoClassDefFoundError` can be thrown. These failures can occur whether Java looks for the class in an installed JAR or in the CLASSPATH. If the Java routine does not catch these errors and exceptions, the routine terminates and an SQL error condition is reported.

Related concepts

"Differences between Java routines and stand-alone Java programs" on page 191
Java routines differ in a few basic ways from stand-alone Java programs.

Related tasks

"Writing a Java stored procedure to return result sets" on page 193
You can write your Java stored procedures to return multiple query result sets to a client program.

Creating external stored procedures (Db2 Application programming and SQL)

Writing an external user-defined function (Db2 Application programming and SQL)

Related reference

"Data types that map to database data types in Java applications" on page 207
To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

Static and non-final variables in a Java routine

Using Java variables that are defined as `static` but not `final` can cause problems for Java routines.

The reasons for those problems are:

- Use of variables that are static and non-final reduces portability.

  Because the ANSI/ISO standard does not include support for static and non-final variables, different database products might process those variables differently.
- A sequence of routine invocations is not necessarily processed by the same JVM, and static variable values are not shared among different JVMs.

  For example, suppose that two stored procedures, INITIALIZE and PROCESS, use the same static variable, sv1. INITIALIZE sets the value of sv1, and PROCESS depends on the value of sv1. If INITIALIZE runs in one JVM, and then PROCESS runs in another JVM, sv1 in PROCESS does not contain the value that INITIALIZE set.

  Specifying NUMTCB=1 in the WLM-established stored process space startup procedure is not sufficient to guarantee that a sequence of routine invocations go to the same JVM. Under load, multiple stored procedure address spaces are initiated, and each address space has its own JVM. Multiple invocations might be directed to multiple address spaces.
- In Java, the static variables for a class are initialized or reset whenever the class is loaded. However, for Java routines, it is difficult to know when initialization or reset of static variables occurs.

In certain cases, you need to declare variables as static and non-final. In those cases, you can use the following technique to make your routines work correctly with static variables.

To determine whether the values of static data in a routine have persisted across routine invocations, define a static boolean variable in the class that contains the routine. Initially set the variable to false, and then set it to true when you set the value of static data. Check the value of the boolean variable at the

beginning of the routine. If the value is true, the static data has persisted. Otherwise, the data values need to be set again. With this technique, static data values are not set for most routine invocations, but are set more than once during the lifetime of the JVM. Also, with this technique, it is not a problem for a routine to execute on different JVMs for different invocations.

Writing a Java stored procedure to return result sets

You can write your Java stored procedures to return multiple query result sets to a client program.

Before you begin

A stored procedure can return multiple query result sets to a client program if the following conditions are satisfied:

- The client supports the DRDA code points that are used to return query result sets.
- The value of DYNAMIC RESULT SETS in the stored procedure definition is greater than 0.

Procedure

For each result set that you want to be returned, your Java stored procedure must perform the following actions:

1. For each result set, include an object of type java.sql.`ResultSet`[] or an array of an SQLJ iterator class in the parameter list for the stored procedure method.

   If the stored procedure definition includes a method signature, for each result set, include java.sql.ResultSet[] or the fully-qualified name of an array of a class that is declared as an SQLJ iterator in the method signature. These result set parameters must be the *last* parameters in the parameter list or method signature. Do *not* include a `java.sql.ResultSet` array or an iterator array in the SQL parameter list of the stored procedure definition.
2. Execute a SELECT statement to obtain the contents of the result set.
3. Retrieve any rows that you do *not* want to return to the client.
4. Assign the contents of the result set to element 0 of the `java.sql.ResultSet`[] object or array of an SQLJ iterator class that you declared in step “1” on page 193.
5. Do not close the `ResultSet`, the statement that generated the `ResultSet`, or the connection that is associated with the statement that generated the `ResultSet`.

   Db2 does not return result sets for `ResultSets` that are closed before the stored procedure terminates.

Example

The following code shows an example of a Java stored procedure that uses an SQLJ iterator to retrieve a result set.

```
package s1;

import sqlj.runtime.*;
import java.sql.*;
import java.math.*;
#sql iterator NameSal(String LastName, BigDecimal Salary);                  1
public class S1Sal
{
  public static void getSals(BigDecimal[] AvgSalParm,
                             java.sql.ResultSet[] rs)                       2
    throws SQLException
  {
    NameSal iter1;
    try
    {
      #sql iter1 = {SELECT LASTNAME, SALARY FROM EMP                        3
                      WHERE SALARY>0 ORDER BY SALARY DESC};
      #sql {SELECT AVG(SALARY) INTO :(AvgSalParm[0]) FROM EMP};             4
    }
    catch (SQLException e)
    {
      System.out.println("SQLCODE returned: " + e.getErrorCode());
      throw(e);
    }
    rs[0] = iter1.getResultSet();                                           5
  }
}
```

Figure 48. Java stored procedure that returns a result set

Notes to Figure 48 on page 194:

Note	Explanation
1	This SQLJ clause declares the iterator named NameSal, which is used to retrieve the rows that will be returned to the stored procedure caller in a result set.
2	The declaration for the stored procedure method contains declarations for a single passed parameter, followed by the declaration for the result set object.
3	This SQLJ clause executes the SELECT to obtain the rows for the result set, constructs an iterator object that contains those rows, and assigns the iterator object to variable iter1.
4	This SQLJ clause retrieves a value into the parameter that is returned to the stored procedure caller.
5	This statement uses the `getResultSet` method to assign the contents of the iterator to the result set that is returned to the caller.

Related concepts

"Retrieving multiple result sets from a stored procedure in an SQLJ application" on page 152
Some stored procedures return one or more result sets to the calling program by including the DYNAMIC RESULT SETS *n* clause in the definition, with *n*>0, and opening cursors that are defined with the WITH RETURN clause. The calling program needs to retrieve the contents of those result sets.

Related tasks

"Retrieving multiple result sets from a stored procedure in a JDBC application" on page 53
If you call a stored procedure that returns result sets, you need to include code to retrieve the result sets.

Techniques for testing a Java routine

You can test your Java routines as stand-alone programs, use the IBM Data Studio routine debugger, or write your own debug information from the routines.

Test your routine as a stand-alone program

Before you invoke your Java routines from SQL applications, it is a good idea to run the routines as stand-alone programs, which are easier to debug. A Java program that runs as a routine requires only a

Db2 package. However, before you can run the program as a stand-alone program, you need to bind a Db2 plan for it.

Use the IBM Data Studio routine debugger (stored procedures only)

The IBM Data Studio routine debugger is available with Db2 Database for Linux, UNIX, and Windows. The IBM Data Studio routine debugger provides a GUI interface for debugging Java stored procedures. For information on the IBM Data Studio routine debugger, see Routine debugger (IBM Data Studio).

To set up a Db2 for z/OS subsystem to work with the IBM Data Studio routine debugger, when you set up your stored procedure environment, follow these additional steps:

1. Customize and run the DSNTIJRT program to define stored procedures that provide server support for the IBM Data Studio routine debugger.

   DSNTIJSD is in the *prefix*.SDSNSAMP data set. The job prolog contains customization instructions.
2. Define the stored procedure that you intend to test with the ALLOW DEBUG MODE option in the CREATE PROCEDURE or ALTER PROCEDURE statement.
3. When you prepare the stored procedure for execution, specify the -g option in the javac command

   -g causes the compiler to generate all debugging information for the program.

   .
4. Grant the DEBUGSESSION privilege to the user who runs the debug client.
5. Make the following modifications to the WLM environment for the stored procedure:
   - In the WLM environment startup procedure, set NUMTCB=1
   - In the WLM environment startup procedure, include a PSMDEBUG DD statement to direct the debug diagnostic log to a data set. You can allocate to a SYSOUT data set or to a preallocated data set. The data set needs to be created with the RECFM=VBA and LRECL=4096 characteristics.
   - In the ENVAR settings in the JAVAENV data set, set USE_LIBJVM_G=YES.
   - If the debug port range of 8000::8050 is not acceptable, in the ENVAR settings in the JAVAENV data set, set JVM_DEBUG_PORTRANGE to the range of ports that the JVM listens on for debug connections.

Enable collection of Db2 debug information

Include a JSPDEBUG DD statement in your startup procedure for the stored procedure address space. This DD statement specifies a data set to which Db2 writes debug information for use by IBM Software Support.

Write your own debug information from your routine

A useful technique for debugging is to include `System.out.println` and `System.err.println` calls in your program to write messages to the STDERR and STDOUT files.

STDERR and STDOUT output is written to the directory that is specified by the WORK_DIR parameter in the JAVAENV data set, if that directory exists. If no WORK_DIR parameter is specified, output goes to the default directory, /tmp/java, if that directory exists.

Related concepts

“Runtime environment for Java routines” on page 180
For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

Chapter 7. Preparing and running JDBC and SQLJ programs

You prepare and run Db2 for z/OS Java programs in the z/OS UNIX System Services environment.

Program preparation for JDBC programs

Preparing a Java program that contains only JDBC methods is the same as preparing any other Java program. You compile the program using the `javac` command. No precompile or bind steps are required.

For example, to prepare the Sample01.java program for execution, execute this command from the /usr/lpp/db2c10/jdbc/ directory:

```
javac Sample01.java
```

Program preparation for SQLJ programs

Program preparation for SQLJ programs involves translating, compiling, customizing, and binding programs.

About this task

The following figure shows the steps of the program preparation process for a program that uses the IBM Data Server Driver for JDBC and SQLJ.



Figure 49. The SQLJ program preparation process

Procedure

The basic steps in SQLJ program preparation are:

1. Run the sqlj command from the z/OS UNIX System Services command line to translate and compile the source code.

   The SQLJ command generates a Java source program, optionally compiles the Java source program, and produces zero or more serialized profiles. You can compile the Java program separately, but the default behavior of the sqlj command is to compile the program. The SQLJ command runs without connecting to the database server.

© Copyright IBM Corp. 1998, 2017

2. Run the db2sqljcustomize command from the z/OS UNIX System Services command line to customize the serialize profiles and bind Db2 packages.

   The db2sqljcustomize command performs these tasks:

   - Customizes the serialized profiles.
   - Optionally does online checking to ensure that application variable types are compatible with the corresponding column data types.

     The default behavior is to do online checking. For better performance, you should do online checking.
   - Optionally binds Db2 packages on a specified database server.

     The default behavior is to bind the Db2 packages. However, you can disable automatic creation of packages and use the db2sqljbind command to bind the packages later.

     You might also need to run the db2sqljbind command under these circumstances:

     – If a bind fails when db2sqljcustomize runs
     – if you want to create identical packages at multiple locations for the same serialized profile
3. Optional: Bind the Db2 packages into a plan.

   Use the Db2 BIND command to do that.

Related reference

“sqlj - SQLJ translator” on page 512
The sqlj command translates an SQLJ source file into a Java source file and zero or more SQLJ serialized profiles. By default, the sqlj command also compiles the Java source file.

“db2sqljbind - SQLJ profile binder” on page 526
db2sqljbind binds Db2 packages for a serialized profile that was previously customized with the db2sqljcustomize command.

“db2sqljcustomize - SQLJ profile customizer” on page 516
db2sqljcustomize processes an SQLJ profile, which contains embedded SQL statements.

Binding SQLJ applications to access multiple database servers

After you prepare an SQLJ program to run on one Db2 database server, you might want to port that application to other environments that access different database servers. For example, you might want to move your application from a test environment to a production environment.

Procedure

The general steps for enabling access of an existing SQLJ application to additional database servers are:

1. Bind packages on each database server that you want to access.

   Do not re-customize the serialized profiles. Customization stores a new package timestamp in the serialized profile, which makes the new serialized profile incompatible with the original package.

   You can use one of the following methods to bind the additional Db2 packages:

   - Run the db2sqljbind command against each of the database servers.
   - Run the Db2 BIND PACKAGE command with the COPY option to copy the original packages to each of the additional database servers.

   You might need a different qualifier for unqualified Db2 objects on each of the database servers. In that case, you need to specify a value for the QUALIFIER bind option when you bind the new packages. If you use the db2sqljbind command, you specify the QUALIFIER option in the -bindoptions parameter, not in the -qualifier parameter. The -qualifier parameter applies to online checking only.
2. Specify the package collection for the Db2 packages.

By default, when an SQLJ application runs, the Db2 database server looks for packages using the collection ID that is stored in the serialized profile. If the collection ID for the additional Db2 packages that you create is different from the collection ID in the serialized profile, you need to override the collection ID that is in the serialized profile. You can do that in one of the following ways:

- Specify the collection ID with the pkList `DataSource` property or the db2.jcc.pkList global property.
- Follow these steps:
  a. Bind a plan for the application that includes the following packages:
     – The package collection that you bound in the previous step
     – The IBM Data Server Driver for JDBC and SQLJ packages
  b. Specify the plan name in the planName `DataSource` property or the db2.jcc.planName global property.

  Binding a plan might simplify authorization for the application. You can authorize users to execute the plan, rather than authorizing them to execute each of the packages in the plan.

Example

An existing SQLJ application was customized and bound using the following db2sqljcustomize invocation:

```
db2sqljcustomize -url jdbc:db2://system1.svl.ibm.com:8000/ZOS1
 -user user01 -password mypass
 -rootPkgName WRKSQLJ
 -qualifier WRK1
 -collection MYCOL1
 -bindoptions "CURRENTDATA NO QUALIFIER WRK1 "
 -staticpositioned YES  WrkTraceTest_SJProfile0.ser
```

In addition to accessing data at the location that is indicated by URL jdbc:db2://system1.svl.ibm.com:8000/ZOS1, you want to use the application to access data at the location that is indicated by jdbc:db2://system2.svl.ibm.com:8000/ZOS2. On the ZOS2 system, Db2 objects have a qualifier of WRK2, and the packages need to be in collection MYCOL2. You therefore need to bind packages at location ZOS2, change the default qualifier to WRK2, and specify the MYCOL2 collection for the packages. Use one of the following methods to bind the packages:

- Run Db2 BIND with COPY to copy each of the packages (one for each isolation level) from the ZOS1 system to the ZOS2 system:

```
BIND PACKAGE (ZOS2.MYCOL2) OWNER(USER01) QUALIFIER(WRK2) -
 COPY(MYCOL.WRKSQLJ1) CURRENTDATA(NO)
BIND PACKAGE (ZOS2.MYCOL2) OWNER(USER01) QUALIFIER(WRK2) -
 COPY(MYCOL.WRKSQLJ2) CURRENTDATA(NO)
BIND PACKAGE (ZOS2.MYCOL2) OWNER(USER01) QUALIFIER(WRK2) -
 COPY(MYCOL.WRKSQLJ3) CURRENTDATA(NO)
BIND PACKAGE (ZOS2.MYCOL2) OWNER(USER01) QUALIFIER(WRK2) -
 COPY(MYCOL.WRKSQLJ4) CURRENTDATA(NO)
```

- Run the db2sqljbind command to create Db2 packages on ZOS2 from the serialized profile on ZOS1:

```
db2sqljbind -url jdbc:db2://system2.svl.ibm.com:8000/ZOS2
 -user user01     -password mypass
 -bindoptions "COLLECTION MYCOL2 QUALIFIER WRK2"
    -staticpositioned YES WrkTraceTest_SJProfile0.ser
```

After you bind the packages, you need to ensure that when the application runs, the Db2 database server at ZOS2 can find the packages. The collection ID in the serialized profile is MYCOL1, so the Db2 database server looks in MYCOL1 for the packages. When you run the application against the ZOS2 system, you need to access packages in MYCOL2.

For applications that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, use one of the following methods to tell the database server to look in MYCOL2 as well as MYCOL1:

- Specify "MYCOL1.*,MYCOL2.*" in the pkList DataSource property:

```
pkList = MYCOL1.*,MYCOL2.*
```

- Bind a plan for the application that includes the packages in MYCOL2 and the IBM Data Server Driver for JDBC and SQLJ packages:

```
BIND PLAN(WRKSQLJ) PKLIST(MYCOL1.*,MYCOL2.*,JDBCCOL.*)
```

  Then specify WRKSQLJ in the planName DataSource property:

```
planName = WRKSQLJ
```

For applications that use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, specify "MYCOL1,MYCOL2" in the currentPackagePath DataSource property.

Related tasks

"Program preparation for SQLJ programs" on page 197
Program preparation for SQLJ programs involves translating, compiling, customizing, and binding programs.

Related reference

"db2sqljbind - SQLJ profile binder" on page 526
db2sqljbind binds Db2 packages for a serialized profile that was previously customized with the db2sqljcustomize command.

Program preparation for Java routines

The program preparation process for Java routines varies, depending on whether the routines contain SQLJ clauses.

The following topics contain detailed information on program preparation for Java routines.

Preparation of Java routines with no SQLJ clauses

Java routines that contain no SQLJ clauses are written entirely in JDBC. You can use one of three methods to prepare Java routines with no SQLJ statements.

Those methods are:

- Prepare the Java routine to run from a JAR file. Running Java routines from JAR files is recommended.
- Prepare the Java routine with no JAR file.
- Use IBM Optim Development Studio to prepare the routine.

  You can use this method regardless of whether the routine is in a JAR file.

Preparing Java routines with no SQLJ clauses to run from a JAR file

The recommended method of running Java routines is to run them from a JAR file.

About this task

The steps in this task prepare a JDBC routine for execution, create a JAR file for the routine, define the JAR file and routine to Db2, and grant access on the routine to users.

Procedure

1. Run the javac command to compile the Java program to produce Java bytecodes.
2. Run the `jar` command to collect the class files that contain the methods for your routine into a JAR file. See 'Creating JAR files for Java routines" for information on creating the JAR file.
3. Call the INSTALL_JAR stored procedure to define the JAR file to Db2.

4. If the installed JAR references classes in other installed JARs, call the SQLJ.ALTER_JAVA_PATH stored procedure to specify the class resolution path that the JVM searches to resolve those class references.
5. If another user defines the routine to Db2, execute the SQL GRANT USAGE ON JAR statement to grant the privilege to use the JAR file to that user.
6. Execute the SQL CREATE PROCEDURE or CREATE FUNCTION statement to define the routine to Db2. Specify the EXTERNAL NAME parameter with the name of the JAR that you defined to Db2 in step "3" on page 200.
7. Execute the SQL GRANT statement to grant the EXECUTE privilege on the routine to the appropriate users.

Related concepts

"Program preparation for JDBC programs" on page 197
Preparing a Java program that contains only JDBC methods is the same as preparing any other Java program. You compile the program using the `javac` command. No precompile or bind steps are required.

"Definition of a JAR file for a Java routine to Db2" on page 190
One way to organize the classes for a Java routine is to collect those classes into a JAR file. If you do this, you need to install the JAR file into the Db2 catalog.

Related tasks

"Creating JAR files for Java routines" on page 205
A convenient way to ensure that all modules of a Java routine are accessible is to store those modules in a JAR file. You create the JAR file by running the `jar` command in z/OS UNIX System Services.

Preparing Java routines with no SQLJ clauses and no JAR file

If you do not use a JAR file for a Java routine that has no SQLJ clauses, you need to include the directories for the routine classes in the CLASSPATH.

About this task

The steps in this task compile source code, add the locations of the resulting class files to the CLASSPATH, define the routine to Db2, and grant access on the routine to users.

Procedure

1. Run the javac command to compile the Java program to produce Java bytecodes.
2. Ensure that the zFS or HFS directory that contains the class files for your routine is in the CLASSPATH for the WLM-established stored procedure address space.

   You specify this CLASSPATH in the JAVAENV data set. You specify the JAVAENV data set using a JAVAENV DD statement in the startup procedure for the WLM-established stored procedure address space.

   If you need to modify the CLASSPATH environment variable in the JAVAENV data set to include the directory for the Java routine's classes, you must restart the WLM address space to make it use the modified CLASSPATH.
3. Execute the SQL CREATE PROCEDURE or CREATE FUNCTION statement to define the routine to Db2. Specify the EXTERNAL NAME parameter without a JAR name.
4. Execute the SQL GRANT statement to grant the EXECUTE privilege on the routine to the appropriate users.

Related concepts

"Program preparation for JDBC programs" on page 197
Preparing a Java program that contains only JDBC methods is the same as preparing any other Java program. You compile the program using the `javac` command. No precompile or bind steps are required.

"Runtime environment for Java routines" on page 180

For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

Preparation of Java routines with SQLJ clauses

You can use one of three methods to prepare Java routines with SQLJ clauses.

Those methods are:

- Prepare the routine Java routine to run from a JAR file. Running Java routines from JAR files is recommended.
- Prepare the routine Java routine with no JAR file.
- Use IBM Optim Development Studio to prepare the routine.

  You can use this method regardless of whether the routine is in a JAR file.

Preparing Java routines with SQLJ clauses to run from a JAR file

The recommended method of running Java routines with SQLJ clauses is to run them from a JAR file.

About this task

The steps in this task prepare an SQLJ routine for execution, create JAR files for the methods in the routine, define the JAR files to Db2, define the routine to Db2, and grant access on the routine to users.

Procedure

1. Run the sqlj command to translate the source code to produce generated Java source code and serialized profiles, and to compile the Java program to produce Java bytecodes.
2. Run the `db2sqljcustomize` command to produce serialized profiles that are customized for Db2 for z/OS and Db2 packages.
3. Run the `jar` command to package the class files that contain the methods for your routine, and the profiles that you generated in step “2” on page 202 into a JAR file. See "Creating JAR files for Java routines" for information on creating the JAR file.
4. Call the INSTALL_JAR stored procedure to define the JAR file to Db2.
5. If the installed JAR references classes in other installed JARs, call the SQLJ.ALTER_JAVA_PATH stored procedure to specify the class resolution path that the JVM searches to resolve those class references.
6. If another user defines the routine to Db2, execute the SQL GRANT USAGE ON JAR statement to grant the privilege to use the JAR file to that user.
7. Execute the SQL CREATE PROCEDURE or CREATE FUNCTION statement to define the routine to Db2. Specify the EXTERNAL NAME parameter with the name of the JAR that you defined to Db2 in step “4” on page 202.
8. Execute the SQL GRANT statement to grant the EXECUTE privilege on the routine to the appropriate users.

Example

The following example demonstrates how to prepare a Java stored procedure that contains SQLJ clauses for execution from a JAR file.

1. On z/OS UNIX System Services, run the `sqlj` command to translate and compile the SQLJ source code.

   Assume that the path for the stored procedure source program is /u/db2res3/s1/s1sal.sqlj. Change to directory /u/db2res3/s1, and issue this command:

   ```
   sqlj s1sal.sqlj
   ```

After this process completes, the /u/db2res3/s1 directory contains these files:

```
s1sal.java
s1sal.class
s1sal_SJProfile0.ser
```

2. On z/OS UNIX System Services, run the `db2sqljcustomize` command to produce serialized profiles that are customized for Db2 for z/OS and to bind the Db2 packages for the stored procedure.

   Change to the /u/db2res3 directory, and issue this command:

   ```
   db2sqljcustomize -url jdbc:db2://mvs1:446/SJCEC1 \
     -user db2adm -password db2adm \
     -bindoptions "EXPLAIN YES" \
     -collection ADMCOLL \
     -rootpkgname S1SAL \
     s1sal_SJProfile0.ser
   ```

   After this process completes, s1sal_SJProfile0.ser contains a customized serialized profile. The Db2 subsystem contains these packages:

   ```
   S1SAL1
   S1SAL2
   S1SAL3
   S1SAL4
   ```

3. On z/OS UNIX System Services, run the `jar` command to package the class files that you created in step "1" on page 202 and the customized serialized profile that you created in step "2" on page 203 into a JAR file.

   Change to the /u/db2res3 directory, and issue this command:

   ```
   jar -cvf s1sal.jar s1/*.class s1/*.ser
   ```

   After this process completes, the /u/db2res3 directory contains this file:

   ```
   s1sal.jar
   ```

4. Call the INSTALL_JAR stored procedure, which is on Db2 for z/OS, to define the JAR file to Db2.

   You need to execute the CALL statement from a static SQL program or from an ODBC or JDBC program. The CALL statement looks similar to this:

   ```
   CALL SQLJ.INSTALL_JAR('file:/u/db2res3/s1sal.jar','MYSCHEMA.S1SAL',0);
   ```

   The exact form of the CALL statement depends on the language of the program that issues the CALL statement.

   After this process completes, the Db2 catalog contains JAR file MYSCHEMA.S1SAL.

5. If the installed JAR references classes in other installed JARs, call the SQLJ.ALTER_JAVA_PATH stored procedure, which is on Db2 for z/OS, to specify the class resolution path that the JVM searches to resolve those class references. You need to execute the CALL statement from a static SQL program or from an ODBC or JDBC program.
6. If another user defines the routine to Db2, on Db2 for z/OS, execute the SQL GRANT USAGE ON JAR statement to grant the privilege to use the JAR file to that user.

   Suppose that you want any user to be able to define the stored procedure to Db2. This means that all users need the USAGE privilege on JAR MYSCHEMA.S1SAL. To grant this privilege, execute this SQL statement:

   ```
   GRANT USAGE ON JAR MYSCHEMA.S1SAL TO PUBLIC;
   ```

7. On Db2 for z/OS, execute the SQL CREATE PROCEDURE statement to define the stored procedure to Db2:

```
CREATE PROCEDURE SYSPROC.S1SAL
 (DECIMAL(10,2) INOUT)
  FENCED
  MODIFIES SQL DATA
  COLLID ADMCOLL
  LANGUAGE JAVA
  EXTERNAL NAME  'MYSCHEMA.S1SAL:s1.S1Sal.getSals'
  WLM ENVIRONMENT WLMIJAV
  DYNAMIC RESULT SETS 1
  PROGRAM TYPE SUB
  PARAMETER STYLE JAVA;
```

8. On Db2 for z/OS, execute the SQL GRANT EXECUTE statement to grant the privilege to run the routine to that user.

   Suppose that you want any user to be able to run the routine. This means that all users need the EXECUTE privilege on SYSPROC.S1SAL. To grant this privilege, execute this SQL statement:

```
GRANT EXECUTE ON PROCEDURE SYSPROC.S1SAL TO PUBLIC;
```

Related concepts

“Definition of a JAR file for a Java routine to Db2” on page 190
One way to organize the classes for a Java routine is to collect those classes into a JAR file. If you do this, you need to install the JAR file into the Db2 catalog.

Related tasks

“Program preparation for SQLJ programs” on page 197
Program preparation for SQLJ programs involves translating, compiling, customizing, and binding programs.

“Creating JAR files for Java routines” on page 205
A convenient way to ensure that all modules of a Java routine are accessible is to store those modules in a JAR file. You create the JAR file by running the `jar` command in z/OS UNIX System Services.

Preparing Java routines with SQLJ clauses and no JAR file

If you do not use a JAR file for a Java routine that contains SQLJ clauses, you need to include the directories for the routine classes in the CLASSPATH.

About this task

The steps in this task prepare an SQLJ routine for execution, specify the class files for the routine in the CLASSPATH, define the routine to Db2, and grant access on the routine to users.

Procedure

1. Run the sqlj command to translate the source code to produce generated Java source code and serialized profiles, and to compile the Java program to produce Java bytecodes.
2. Run the db2sqljcustomize command to produce serialized profiles that are customized for Db2 for z/OS and Db2 packages.
3. Ensure that the zFS or HFS directory that contains the class files for your routine is in the CLASSPATH for the WLM-established stored procedure address space.

   You specify this CLASSPATH in the JAVAENV data set. You specify the JAVAENV data set using a JAVAENV DD statement in the startup procedure for the WLM-established stored procedure address space.

   If you need to modify the CLASSPATH environment variable in the JAVAENV data set to include the directory for the Java routine's classes, you must restart the WLM address space to make it use the modified CLASSPATH.

4. Use the SQL CREATE PROCEDURE or CREATE FUNCTION statement to define the routine to Db2. Specify the EXTERNAL NAME parameter without a JAR name.
5. Execute the SQL GRANT statement to grant the EXECUTE privilege on the routine to the appropriate users.

Related concepts

"Runtime environment for Java routines" on page 180
For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

Related tasks

"Program preparation for SQLJ programs" on page 197
Program preparation for SQLJ programs involves translating, compiling, customizing, and binding programs.

Creating JAR files for Java routines

A convenient way to ensure that all modules of a Java routine are accessible is to store those modules in a JAR file. You create the JAR file by running the `jar` command in z/OS UNIX System Services.

Before you begin

For a JDBC routine, before you can create a JAR file, you need to compile the source code. For an SQLJ routine, before you can create a JAR file, you need to translate, compile, and customize the source code.

Procedure

1. If the Java source file does not contain a `package` statement, change to the directory that contains the class file for the Java routine, which you created by running the javac command.

   For example, if JDBC routine Add_customer.java is in /u/db2res3/acmejos, change to directory /u/db2res3/acmejos.

   If the Java source file contains a `package` statement, change to the directory that is one level above the directory that is named in the `package` statement.

   For example, suppose the package statement is:

   ```
   package lvlOne.lvlTwo.lvlThree;
   ```

   Change to the directory that contains lvlOne as an immediate subdirectory.
2. Run the `jar` command.

   You might need to specify at least these options:

   c
   Creates a new or empty archive.

   v
   Generates verbose output on `stderr`.

   f
   Specifies that the argument immediately after the options list is the name of the JAR file to be created.

   For example, to create a JAR file named acmejos.jar from Add_customer.class, which is in package acmejos, execute this `jar` command:

   ```
   jar -cvf acmejos.jar acmejos/Add_customer.class
   ```

   To create a JAR file for an SQLJ routine, you also need to include all generated class files, such as classes that are generated for iterators, and all serialized profile files. For example, suppose that all classes are declared to be in package acmejos, and all class files, including generated class files, and

all serialized profile files for SQLJ routine Add_customer.sqlj are in directory /u/db2res3/acmejos/. To create a JAR file named acmejos.jar, change the the /u/db2res3 directory, and then issue this `jar` command:

```
jar -cvf acmejos.jar acmejos/*.class acmejos/*.ser
```

Running JDBC and SQLJ programs

You run a JDBC or SQLJ program using the java command. Before you run the program, you need to ensure that the JVM can find all of the files that it needs.

About this task

These steps allow you to run a JDBC or SQLJ program.

Procedure

1. Ensure that the program files can be found.
   - For an SQLJ program, put the serialized profiles for the program in the same directory as the class files for the program.
   - Include directories for the class files that are used by the program in the CLASSPATH.
2. Run the java command on the z/OS UNIX System Services command line, with the top-level file name in the program as the argument.

Example

To run a program that is in the EzJava class, add the directory that contains EzJava to the CLASSPATH. Then run this command:

```
java EzJava
```

Related concepts

"Environment variables for the IBM Data Server Driver for JDBC and SQLJ" on page 534
If you set specific environment variables, the operating system can locate the IBM Data Server Driver for JDBC and SQLJ.

Chapter 8. JDBC and SQLJ reference information

The IBM implementations of JDBC and SQLJ provide a number of application programming interfaces, properties, and commands for developing JDBC and SQLJ applications.

Data types that map to database data types in Java applications

To write efficient JDBC and SQLJ programs, you need to use the best mappings between Java data types and table column data types.

The following tables summarize the mappings of Java data types to JDBC and database data types for a Db2 on Linux, UNIX, and Windows systems, Db2 for z/OS, or IBM Informix system.

Data types for updating table columns

The following table summarizes the mappings of Java data types to database data types for `PreparedStatement.setXXX` or `ResultSet.updateXXX` methods in JDBC programs, and for input host expressions in SQLJ programs. When more than one Java data type is listed, the first data type is the recommended data type.

Table 29. Mappings of Java data types to data server data types for updating database tables

Java data type	Database data type
short, java.lang.Short	SMALLINT
boolean"1" on page 209, byte"1" on page 209, java.lang.Boolean, java.lang.Byte	SMALLINT
int, java.lang.Integer	INTEGER
long, java.lang.Long	BIGINT"13" on page 209
java.math.BigInteger	BIGINT"12" on page 209
java.math.BigInteger	CHAR(*n*)"12" on page 209,"5" on page 209
float, java.lang.Float	REAL
double, java.lang.Double	DOUBLE
java.math.BigDecimal	DECIMAL(*p*,*s*)"2" on page 209
java.math.BigDecimal	DECFLOAT(*n*)"3" on page 209,"4" on page 209
java.lang.String	CHAR(*n*)"5" on page 209
java.lang.String	GRAPHIC(*m*)"6" on page 209
java.lang.String	VARCHAR(*n*)"7" on page 209
java.lang.String	VARGRAPHIC(*m*)"8" on page 209
java.lang.String	CLOB"9" on page 209
java.lang.String	XML"11" on page 209
byte[]	CHAR(*n*) FOR BIT DATA"5" on page 209
byte[]	VARCHAR(*n*) FOR BIT DATA"7" on page 209
byte[]	BINARY(*n*)"5" on page 209, "14" on page 209
byte[]	VARBINARY(*n*)"7" on page 209, "14" on page 209

© Copyright IBM Corp. 1998, 2017

Table 29. Mappings of Java data types to data server data types for updating database tables (continued)

Java data type	Database data type
byte[]	BLOB"9" on page 209
byte[]	ROWID
byte[]	XML"11" on page 209
java.sql.Blob	BLOB
java.sql.Blob	XML"11" on page 209
java.sql.Clob	CLOB
java.sql.Clob	DBCLOB"10" on page 209
java.sql.NClob	DBCLOB"10" on page 209
java.sql.Clob	XML"11" on page 209
java.sql.Date	DATE
java.sql.Time	TIME
java.sql.Timestamp	TIMESTAMP, TIMESTAMP(*p*), TIMESTAMP WITH TIME ZONE, TIMESTAMP(*p*) WITH TIME ZONE"15" on page 209,"16" on page 209
java.io.ByteArrayInputStream	BLOB
java.io.StringReader	CLOB
java.io.ByteArrayInputStream	CLOB
java.io.InputStream	XML"11" on page 209
com.ibm.db2.jcc.DB2RowID (deprecated)	ROWID
java.sql.RowId	ROWID
com.ibm.db2.jcc.DB2Xml (deprecated)	XML"11" on page 209
java.sql.SQLXML	XML"11" on page 209
java.util.Date	CHAR(*n*)"12" on page 209,"5" on page 209
java.util.Date	VARCHAR(*n*)"12" on page 209,"5" on page 209
java.util.Date	DATE"12" on page 209
java.util.Date	TIME"12" on page 209
java.util.Date	TIMESTAMP, TIMESTAMP(*p*), TIMESTAMP WITH TIME ZONE, TIMESTAMP(*p*) WITH TIME ZONE"12" on page 209,"15" on page 209, "16" on page 209
java.util.Calendar	CHAR(*n*)"12" on page 209,"5" on page 209
java.util.Calendar	VARCHAR(*n*)"12" on page 209,"5" on page 209
java.util.Calendar	DATE"12" on page 209
java.util.Calendar	TIME"12" on page 209
java.util.Calendar	TIMESTAMP, TIMESTAMP(*p*), TIMESTAMP WITH TIME ZONE, TIMESTAMP(*p*) WITH TIME ZONE"12" on page 209,"15" on page 209, "16" on page 209

Table 29. Mappings of Java data types to data server data types for updating database tables (continued)

Java data type	Database data type

Notes:

1. For column updates, the data server has no exact equivalent for the Java boolean or byte data types, but the best fit is SMALLINT.
2. *p* is the decimal precision and *s* is the scale of the table column.

   You should design financial applications so that java.math.BigDecimal columns map to DECIMAL columns. If you know the precision and scale of a DECIMAL column, updating data in the DECIMAL column with data in a java.math.BigDecimal variable results in better performance than using other combinations of data types.
3. *n*=16 or *n*=34.
4. DECFLOAT is valid for connections to Db2 for z/OS, Db2 on Linux, UNIX, and Windows systems, or Db2 for IBM i data servers. Use of DECFLOAT requires the SDK for Java Version 5 (1.5) or later.
5. *n*<=255.
6. *m*<=127.
7. *n*<=32704.
8. *m*<=16352.
9. This mapping is valid only if the data server can determine the data type of the column.
10. Use java.sql.Clob if property useJDBC4DataType is set to DB2BaseDataSource.NO. Use java.sql.NClob if property useJDBC4DataType is not set or is set to DB2BaseDataSource.YES.
11. XML is valid for connections to Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems data servers.
12. This mapping is valid only for IBM Data Server Driver for JDBC and SQLJ version 4.13 or later.
13. BIGINT is valid for connections to Db2 for z/OS data servers, Db2 on Linux, UNIX, and Windows systems data servers, and Db2 for IBM i data servers.
14. BINARY and VARBINARY are valid for connections to Db2 for z/OS data servers, Db2 for IBM i 5/OS V5R3 or later data servers, or Db2 on Linux, UNIX, and Windows systems data servers.
15. *p* indicates the timestamp precision, which is the number of digits in the fractional part of the timestamp. 0<=*p*<=12. The default is 6. TIMESTAMP(*p*) is supported for connections to Db2 on Linux, UNIX, and Windows systems and Db2 for z/OS.
16. The WITH TIME ZONE clause is supported for connections to Db2 for z/OS only.

Data types for retrieval from table columns

The following table summarizes the mappings of Db2 or IBM Informix data types to Java data types for `ResultSet.getXXX` methods in JDBC programs, and for iterators in SQLJ programs. This table does not list Java numeric wrapper object types, which are retrieved using `ResultSet.getObject`.

Table 30. Mappings of data server data types to Java data types for retrieving data from data server tables

SQL data type	Recommended Java data type or Java object type	Other supported Java data types
SMALLINT	short	byte, int, long, float, double, java.math.BigDecimal, boolean, java.lang.String
INTEGER	int	short, byte, long, float, double, java.math.BigDecimal, boolean, java.lang.String

Table 30. Mappings of data server data types to Java data types for retrieving data from data server tables (continued)

SQL data type	Recommended Java data type or Java object type	Other supported Java data types
BIGINT"6" on page 211	long	int, short, byte, float, double, java.math.BigDecimal, boolean, java.lang.String
DECIMAL(*p*,*s*) or NUMERIC(*p*,*s*)	java.math.BigDecimal	long, int, short, byte, float, double, boolean, java.lang.String
DECFLOAT(*n*)"1" on page 211,"2" on page 211	java.math.BigDecimal	long, int, short, byte, float, double, java.math.BigDecimal, boolean, java.lang.String
REAL	float	long, int, short, byte, double, java.math.BigDecimal, boolean, java.lang.String
DOUBLE	double	long, int, short, byte, float, java.math.BigDecimal, boolean, java.lang.String
CHAR(*n*)	java.lang.String	long, int, short, byte, float, double, java.math.BigDecimal, boolean, java.sql.Date, java.sql.Time, java.sql.Timestamp, java.io.InputStream, java.io.Reader
VARCHAR(*n*)	java.lang.String	long, int, short, byte, float, double, java.math.BigDecimal, boolean, java.sql.Date, java.sql.Time, java.sql.Timestamp, java.io.InputStream, java.io.Reader
CHAR(*n*) FOR BIT DATA	byte[]	java.lang.String, java.io.InputStream, java.io.Reader
VARCHAR(*n*) FOR BIT DATA	byte[]	java.lang.String, java.io.InputStream, java.io.Reader
BINARY(*n*)"7" on page 211	byte[]	None
VARBINARY(*n*)"7" on page 211	byte[]	None
GRAPHIC(*m*)	java.lang.String	long, int, short, byte, float, double, java.math.BigDecimal, boolean, java.sql.Date, java.sql.Time, java.sql.Timestamp, java.io.InputStream, java.io.Reader

Table 30. Mappings of data server data types to Java data types for retrieving data from data server tables (continued)

SQL data type	Recommended Java data type or Java object type	Other supported Java data types
VARGRAPHIC(*m*)	java.lang.String	long, int, short, byte, float, double, java.math.BigDecimal, boolean, java.sql.Date, java.sql.Time, java.sql.Timestamp, java.io.InputStream, java.io.Reader
CLOB(*n*)	java.sql.Clob	java.lang.String
BLOB(*n*)	java.sql.Blob	byte[]"3" on page 211
DBCLOB(*m*)	No exact equivalent."5" on page 211	
ROWID	java.sql.RowId	byte[], com.ibm.db2.jcc.DB2RowID (deprecated)
XML"4" on page 211	java.sql.SQLXML	byte[], java.lang.String, java.io.InputStream, java.io.Reader
DATE	java.sql.Date	java.sql.String, java.sql.Timestamp
TIME	java.sql.Time	java.sql.String, java.sql.Timestamp
TIMESTAMP, TIMESTAMP(*p*), TIMESTAMP WITH TIME ZONE, TIMESTAMP(*p*) WITH TIME ZONE"8" on page 211,"9" on page 211	java.sql.Timestamp	java.sql.String, java.sql.Date, java.sql.Time, java.sql.Timestamp

Notes:

1. *n*=16 or *n*=34.
2. DECFLOAT is valid for connections to Db2 for z/OS, Db2 on Linux, UNIX, and Windows systems, or Db2 for IBM i data servers. Use of DECFLOAT requires the SDK for Java Version 5 (1.5) or later.
3. This mapping is valid only if the data server can determine the data type of the column.
4. XML is valid for connections to Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems data servers.
5. Use java.sql.Clob if property useJDBC4DataType is set to DB2BaseDataSource.NO. Use java.sql.NClob if property useJDBC4DataType is not set or is set to DB2BaseDataSource.YES.
6. BIGINT is valid for connections to Db2 for z/OS data servers, Db2 on Linux, UNIX, and Windows systems data servers, and all supported Db2 for IBM i data servers.
7. BINARY and VARBINARY are valid for connections to Db2 for z/OS data servers, Db2 for IBM i 5/OS V5R3 and later data servers, or Db2 on Linux, UNIX, and Windows systems data servers.
8. *p* indicates the timestamp precision, which is the number of digits in the fractional part of the timestamp. 0<=*p*<=12. The default is 6. TIMESTAMP(*p*) is supported for connections to Db2 on Linux, UNIX, and Windows systems V9.7 and later and Db2 for z/OS V10 and later only.
9. The WITH TIME ZONE clause is supported for connections to Db2 for z/OS only.

Data types for calling stored procedures and user-defined functions

The following table summarizes mappings of Java data types to JDBC data types and Db2 or IBM Informix data types for calling user-defined function and stored procedure parameters. The mappings of Java data types to JDBC data types are for `CallableStatement.registerOutParameter` methods in JDBC programs. The mappings of Java data types to data server data types are for parameters in stored procedure or user-defined function invocations.

If more than one Java data type is listed in the following table, the first data type is the **recommended** data type.

Table 31. Mappings of Java, JDBC, and SQL data types for calling stored procedures and user-defined functions

Java data type	JDBC data type	SQL data type "1" on page 213
boolean "2" on page 213, java.lang.Boolean	BIT	SMALLINT
byte "2" on page 213, java.lang.Byte	TINYINT	SMALLINT
short, java.lang.Short	SMALLINT	SMALLINT
int, java.lang.Integer	INTEGER	INTEGER
long, java.lang.Long	BIGINT	BIGINT "6" on page 213
float, java.lang.Float	REAL	REAL
float, java.lang.Float	FLOAT	REAL
double, java.lang.Double	DOUBLE	DOUBLE
java.math.BigDecimal	DECIMAL	DECIMAL
java.math.BigDecimal	java.types.OTHER	DECFLOAT*n* "3" on page 213
java.math.BigDecimal	com.ibm.db2.jcc.DB2Types.DECFLOAT	DECFLOAT*n* "3" on page 213
java.lang.String	CHAR	CHAR
java.lang.String	CHAR	GRAPHIC
java.lang.String	VARCHAR	VARCHAR
java.lang.String	VARCHAR	VARGRAPHIC
java.lang.String	LONGVARCHAR	VARCHAR
java.lang.String	VARCHAR	CLOB
java.lang.String	LONGVARCHAR	CLOB
java.lang.String	CLOB	CLOB
byte[]	BINARY	CHAR FOR BIT DATA
byte[]	VARBINARY	VARCHAR FOR BIT DATA
byte[]	BINARY	BINARY "5" on page 213
byte[]	VARBINARY	VARBINARY "5" on page 213
byte[]	LONGVARBINARY	VARCHAR FOR BIT DATA
byte[]	VARBINARY	BLOB "4" on page 213
byte[]	LONGVARBINARY	BLOB "4" on page 213
java.sql.Date	DATE	DATE

Table 31. Mappings of Java, JDBC, and SQL data types for calling stored procedures and user-defined functions (continued)

Java data type	JDBC data type	SQL data type"1" on page 213
java.sql.Time	TIME	TIME
java.sql.Timestamp	TIMESTAMP	TIMESTAMP, TIMESTAMP(*p*), TIMESTAMP WITH TIME ZONE, TIMESTAMP(*p*) WITH TIME ZONE"7" on page 213,"8" on page 213
java.sql.Blob	BLOB	BLOB
java.sql.Clob	CLOB	CLOB
java.sql.Clob	CLOB	DBCLOB
java.io.ByteArrayInputStream	None	BLOB
java.io.StringReader	None	CLOB
java.io.ByteArrayInputStream	None	CLOB
com.ibm.db2.jcc.DB2RowID (deprecated)	com.ibm.db2.jcc.DB2Types.ROWID	ROWID
java.sql.RowId	java.sql.Types.ROWID	ROWID
java.sql.SQLXML	java.sql.Types.SQLXML	XML
java.sql.ResultSet	com.ibm.db2.jcc.DB2Types.CURSOR	CURSOR type

Notes:

1. A Db2 for z/OS stored procedure or user-defined function parameter cannot have the XML data type.
2. A stored procedure or user-defined function that is defined with a SMALLINT parameter can be invoked with a boolean or byte parameter. However, this is not recommended.
3. DECFLOAT parameters in Java routines are valid only for connections to Db2 for z/OS data servers. DECFLOAT parameters in Java routines are not supported for connections to for Linux, UNIX, and Windows or Db2 for IBM i. Use of DECFLOAT requires the SDK for Java Version 5 (1.5) or later.
4. This mapping is valid only if the data server can determine the data type of the column.
5. BINARY and VARBINARY are valid for connections to Db2 for z/OS data servers, Db2 for IBM i 5/OS V5R3 and later data servers, or Db2 on Linux, UNIX, and Windows systems data servers.
6. BIGINT is valid for connections to Db2 for z/OS data servers and Db2 on Linux, UNIX, and Windows systems data servers .
7. *p* indicates the timestamp precision, which is the number of digits in the fractional part of the timestamp. 0<=*p*<=12. The default is 6. TIMESTAMP(*p*) is supported for connections to Db2 on Linux, UNIX, and Windows systems and Db2 for z/OS.
8. The WITH TIME ZONE clause is supported for connections to Db2 for z/OS.

Data types in Java stored procedures and user-defined functions

The following table summarizes mappings of the SQL parameter data types in a CREATE PROCEDURE or CREATE FUNCTION statement to the data types in the corresponding Java stored procedure or user-defined function method.

For Db2 on Linux, UNIX, and Windows systems, if more than one Java data type is listed for an SQL data type, only the **first** Java data type is valid.

For Db2 for z/OS, if more than one Java data type is listed, and you use a data type other than the first data type as a method parameter, you need to include a method signature in the EXTERNAL clause of your CREATE PROCEDURE or CREATE FUNCTION statement that specifies the Java data types of the method parameters.

Table 32. Mappings of SQL data types in a CREATE PROCEDURE or CREATE FUNCTION statement to data types in the corresponding Java stored procedure or user-defined function program

SQL data type in CREATE PROCEDURE or CREATE FUNCTION**"1" on page 215**	**Data type in Java stored procedure or user-defined function method****"2" on page 215**
SMALLINT	short, java.lang.Integer
INTEGER	int, java.lang.Integer
BIGINT"3" on page 215	long, java.lang.Long
REAL	float, java.lang.Float
DOUBLE	double, java.lang.Double
DECIMAL	java.math.BigDecimal
DECFLOAT"4" on page 215	java.math.BigDecimal
CHAR	java.lang.String
VARCHAR	java.lang.String
CHAR FOR BIT DATA	byte[]
VARCHAR FOR BIT DATA	byte[]
BINARY"5" on page 215	byte[]
VARBINARY"5" on page 215	byte[]
DATE	java.sql.Date
TIME	java.sql.Time
TIMESTAMP, TIMESTAMP(*p*), TIMESTAMP WITH TIME ZONE, TIMESTAMP(*p*) WITH TIME ZONE"6" on page 215,"7" on page 215	java.sql.Timestamp
BLOB	java.sql.Blob
CLOB	java.sql.Clob
DBCLOB	java.sql.Clob
ROWID	java.sql.Types.ROWID

Table 32. Mappings of SQL data types in a CREATE PROCEDURE or CREATE FUNCTION statement to data types in the corresponding Java stored procedure or user-defined function program (continued)

SQL data type in CREATE PROCEDURE or CREATE FUNCTION"1" on page 215	Data type in Java stored procedure or user-defined function method"2" on page 215

Notes:

1. A Db2 for z/OS stored procedure or user-defined function parameter cannot have the XML data type.
2. For a stored procedure or user-defined function on a Db2 on Linux, UNIX, and Windows systems server, only the **first** data type is valid.
3. BIGINT is valid for connections to Db2 for z/OS data servers or Db2 on Linux, UNIX, and Windows systems data servers.
4. DECFLOAT parameters in Java routines are valid only for connections to Db2 for z/OS data servers. DECFLOAT parameters in Java routines are not supported for connections to for Linux, UNIX, and Windows or Db2 for IBM i. Use of DECFLOAT requires the SDK for Java Version 5 (1.5) or later.
5. BINARY and VARBINARY are valid for connections to Db2 for z/OS data servers, Db2 for IBM i 5/OS V5R3 or later data servers, or Db2 on Linux, UNIX, and Windows systems data servers.
6. *p* indicates the timestamp precision, which is the number of digits in the fractional part of the timestamp. 0<=*p*<=12. The default is 6. TIMESTAMP(*p*) is supported for connections to Db2 on Linux, UNIX, and Windows systems data servers and Db2 for z/OS data servers.
7. The WITH TIME ZONE clause is supported for connections to Db2 for z/OS data servers.

Date, time, and timestamp values that can cause problems in JDBC and SQLJ applications

You might receive unexpected results in JDBC and SQLJ applications if you use date, time, and timestamp in certain situations.

The following items might cause problems:

- Use of the hour '24' to represent midnight.
- Use of a date between October 5, 1582, and October 14, 1582, inclusive.
- The system on which the data server resides adjusts for daylight saving time.

Problems with using the hour '24' as midnight

The IBM Data Server Driver for JDBC and SQLJ uses Java data types for its internal processing of input and output parameters and `ResultSet` content in JDBC and SQLJ applications. The Java data type that is used by the driver is based on the best match for the corresponding SQL type when the target SQL type is known to the driver.

For values that are assigned to or retrieved from DATE, TIME, or TIMESTAMP SQL types, the IBM Data Server Driver for JDBC and SQLJ uses java.sql.Date for DATE SQL types, java.sql.Time for TIME SQL types, and java.sql.Timestamp for TIMESTAMP SQL types.

When you assign a string value to a DATE, TIME, or TIMESTAMP target, the IBM Data Server Driver for JDBC and SQLJ uses Java facilities to convert the string value to a java.sql.Date, java.sql.Time, or java.sql.Timestamp value. If a string representation of a date, time, or timestamp value does not correspond to a real date or time, Java adjusts the value to a real date or time value. In particular, Java adjusts an hour value of '24' to '00' of the next day. This adjustment can result in an exception for a timestamp value of '9999-12-31 24:00:00.0', because the adjusted year value becomes '10000'.

Important: To avoid unexpected results when you assign or retrieve date, time, or timestamp values in JDBC or SQLJ applications, ensure that the values are real date, time, or timestamp values. In addition, do not use '24' as the hour component of a time or timestamp value.

If a value that does not correspond to a real date or time, such as a value with an hour component of '24', is stored in a TIME or TIMESTAMP column, you can avoid adjustment during retrieval by executing the SQL CHAR function against that column in the SELECT statement that defines a `ResultSet`. Executing the CHAR function converts the date or time value to a character string value on the database side. However, if you use the `getTime` or `getTimestamp` method to retrieve that value from the `ResultSet`, the IBM Data Server Driver for JDBC and SQLJ converts the value to a java.sql.Time or java.sql.Timestamp type, and Java adjusts the value. To avoid date adjustment, execute the CHAR function against the column value, *and* retrieve the value from the `ResultSet` with the `getString` method.

The following examples show the results of updating DATE, TIME, or TIMESTAMP columns in JDBC or SQLJ applications, when the application data does not represent real dates or times.

Table 33. Examples of updating DATE, TIME, or TIMESTAMP SQL values with Java date, time, or timestamp values that do not represent real dates or times

String input value	Target type in database	Value sent to table column, or exception
2008-13-35	DATE	2009-02-04
25:00:00	TIME	01:00:00
24:00:00	TIME	00:00:00
2008-15-36 28:63:74.0	TIMESTAMP	2009-04-06 05:04:14.0
9999-12-31 24:00:00.0	TIMESTAMP	Exception, because the adjusted value (10000-01-01 00:00:00.0) exceeds the maximum year of 9999.

The following examples demonstrate the results of retrieving data from TIMESTAMP columns in JDBC or SQLJ applications, when the values in those columns do not represent real dates or times.

Table 34. Results of retrieving DATE, TIME, or TIMESTAMP SQL values that do not represent real dates or times into Java application variables

SELECT statement	Value in TIMESTAMP column TS_COL	Target type in application (getXXX method for retrieval)	Value retrieved from table column
SELECT TS_COL FROM TABLE1	2000-01-01 24:00:00.000000	java.sql.Timestamp (`getTimestamp`)	2000-01-02 00:00:00.000000
SELECT TS_COL FROM TABLE1	2000-01-01 24:00:00.000000	String (`getString`)	2000-01-02 00:00:00.000000
SELECT CHAR(TS_COL) FROM TABLE1	2000-01-01 24:00:00.000000	java.sql.Timestamp (`getTimestamp`)	2000-01-02 00:00:00.000000
SELECT CHAR(TS_COL) FROM TABLE1	2000-01-01 24:00:00.000000	String (`getString`)	2000-01-01 24:00:00.000000 (no adjustment by Java)

Problems with using dates in the range October 5, 1582, through October 14, 1582

The Java `java.util.Date` and `java.util.Timestamp` classes use the Julian calendar for dates before October 4, 1582, and the Gregorian calendar for dates starting with October 4, 1582. In the Gregorian calendar, October 4, 1582, is followed by October 15, 1582. If a Java program encounters a `java.util.Date` or `java.util.Timestamp` value that is between October 5, 1582, and October 14, 1582, inclusive, Java adds 10 days to that date. Therefore, a DATE or TIMESTAMP value in a Db2 table that has a value between October 5, 1582, and October 14, 1582, inclusive, is retrieved in a Java program as a `java.util.Date` or `java.util.Timestamp` value between October 15, 1582, and October 24,

1582, inclusive. A `java.util.Date` or `java.util.Timestamp` value in a Java program that is between October 5, 1582, and October 14, 1582, inclusive, is stored in a Db2 table as a DATE or TIMESTAMP value between October 15, 1582, and October 24, 1582, inclusive.

Example: Retrieve October 10, 1582, from a DATE column.

```
// DATETABLE has one date column with one row.
// Its value is 1582-10-10.
java.sql.ResultSet rs =
 statement.executeQuery(select * from DATETABLE);
rs.next();
System.out.println(rs.getDate(1)); // Value is retrieved as 1582-10-20
```

Example: Store October 10, 1582, in a DATE column.

```
java.sql.Date d = java.sql.Date.valueOf("1582-10-10");
java.sql.PreparedStatement ps =
 c.prepareStatement("Insert into DATETABLE values(?)");
ps.setDate(1, d);
ps.executeUpdate(); // Value is inserted as 1582-10-20
```

To retrieve a value in the range October 5, 1582, to October 14, 1582, from a Db2 table without date adjustment, execute the SQL CHAR function against the DATE or TIMESTAMP column in the SELECT statement that defines a `ResultSet`. Executing the CHAR function converts the date or time value to a character string value on the database side.

To store a value in the range October 5, 1582, to October 14, 1582 in a Db2 table without date adjustment, you can use one of the following techniques:

- For a JDBC or an SQLJ application, use the `setString` method to assign the value to a String input parameter. Cast the input parameter as VARCHAR, and execute the DATE or TIMESTAMP function against the result of the cast. Then store the result of the DATE or TIMESTAMP function in the DATE or TIMESTAMP column.
- For a JDBC application, set the `Connection` or `DataSource` property sendDataAsIs to **true**, and use the `setString` method to assign the date or timestamp value to the input parameter. Then execute an SQL statement to assign the String value to the DATE or TIMESTAMP column.

Example: Retrieve October 10, 1582, from a DATE column without date adjustment.

```
// DATETABLE has one date column called DATECOL with one row.
// Its value is 1582-10-10.
java.sql.ResultSet rs =
 statement.executeQuery(SELECT CHAR(DATECOL) FROM DATETABLE);
rs.next();
System.out.println(rs.getString(1)); // Value is retrieved as 1582-10-10
```

Example: Store October 10, 1582, in a DATE column without date adjustment.

```
String s = "1582-10-10";
java.sql.Statement stmt = c.createStatement;
java.sql.PreparedStatement ps =
 c.prepareStatement("Insert INTO DATETABLE VALUES " +
  "(DATE(CAST (? AS VARCHAR)))");
ps.setString(1, s);
ps.executeUpdate(); // Value is inserted as 1582-10-10
```

To avoid date adjustment, set the SQLJ option sqljAvoidTimeStampConversion to true. The SQLJ option sqljAvoidTimeStampConversion=true returns the timestamp data in CHAR format.

Example: Retrieve October 12, 1582, from a DATE column without date adjustment.

```
import java.sql.*;
import javax.sql.DataSource;
import sqlj.runtime.ref.DefaultContext;
import com.ibm.db2.jcc.DBTimestamp;
import com.ibm.db2.jcc.DB2BaseDataSource;
#sql context DBContext;

public class UpdateTest
```

```
{
// Set the timestamp conversion off.
static boolean SqljAvoidTimeStampConversion =true;
static DefaultContext ctx = null;
java.sql.Connection con;
 public static void main(String[] args) throws Exception
  {
   javax.sql.DataSource ds = new com.ibm.db2.jcc.DB2SimpleDataSource();
     ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setServerName
                                             ("myserver.svl.ibm.com");
     ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setPortNumber(446);
     ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setDatabaseName("MYDB");
     ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setDriverType(4);
     ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setTimestampOutputType
                                             (DB2BaseDataSource.JCC_DBTIMESTAMP);
     ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setSqljAvoidTimeStampConversion
                                             (true);
       java.sql.Connection con = ds.getConnection("myid", "mypwd");
// Create a connection context instance to pass to the
// insertAndSelectTimestamp method.
     ctx = new DefaultContext(con);
       System.out.println(" Default Context  Obtained Successfully...");
     insertAndSelectTimestamp(ctx);
     }
   public static  void insertAndSelectTimestamp
          (DefaultContext ctx)throws java.sql.SQLException
     {
         String temp = "";
      #sql[ctx]  { CREATE TABLE Mytable (C1 TIMESTAMP(12))};
// Create the table.
      System.out.println ("table created");
      #sql[ctx]  { INSERT INTO Mytable (C1)
                   VALUES('1582-10-12-21.22.33.123456789012') };
// Insert a value in the range October 5, 1582 through October 14, 1582.
// sqljAvoidTimeStampConversion is set to true so the value is stored as is.
      System.out.println ("table inserted");
      #sql[ctx] { COMMIT};
// Retrieve the value you inserted. sqljAvoidTimeStampConversion = true,
// so the timestamp should not be adjusted, and you should get back the
// value that you put in.
      #sql[ctx] { select C1 into :temp from Mytable };
      }
}
```

Problems due to time adjustment for daylight saving time

Some locations observe daylight saving time. That means:

- The clock moves forward by one hour on a specified date in the spring, which makes the length of that day 23 hours.
- The clock moves backward by one hour on a specified date in the fall, which makes the length of that day is 25 hours.

If time adjustment occurs during the hour after the switch to daylight saving time, a timestamp value that is retrieved from a Db2 table in a JDBC or SQLJ program might be incorrect. You can set the `sqljAvoidTimeStampConversion` property to `true` to prevent time adjustment. When you set the sqljAvoidTimeStampConversion property to `true`, you need to use the `ResultSet.getString` method to retrieve timestamp values in `String` format.

Example: Retrieve a timestamp value without time adjustment.

```
import java.io.IOException;
import java.sql.*;
import java.util.Arrays;
import com.ibm.db2.jcc.DB2BaseDataSource;
import java.util.Calendar;

public class TestTimeStamp {
 public static void main(String[] args) throws Exception {
  javax.sql.DataSource ds = new com.ibm.db2.jcc.DB2SimpleDataSource();
  ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setServerName
   ("myserver.svl.ibm.com");
  ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setPortNumber(446);
  ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setDatabaseName("MYDB");
  ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setDriverType(4);
```

```
// Set property setSqljAvoidTimeStampConvertion to true to
// prevent adjustment for daylight saving time during timestamp
// retrieval
  ((com.ibm.db2.jcc.DB2BaseDataSource)
   ds).setSqljAvoidTimeStampConversion(true);
  java.sql.Connection con = ds.getConnection("myid", "mypwd");
  System.out.println("Connected to data server");
  Statement stmt1 = con.createStatement();
  try {
// Drop the test table if it already exists; otherwise, do nothing.
       stmt1.execute("DROP TABLE MYTABLE1");
      } catch (Exception e) {
      }
// Create a test table with a TIMESTAMP column and a
// TIMESTAMP WITH TIME ZONE column.
      stmt1.execute("CREATE TABLE MYTABLE1 " +
       "(TSTAMP1 TIMESTAMP WITH TIME ZONE, " +
       "TSTAMP2 TIMESTAMP)");
// Insert the same timestamp value into the TIMESTAMP WITH
// TIME ZONE column and the TIMESTAMP column so you can see
// the retrieved timestamp values when time adjustment
// is not performed. The inserted timestamp is 15 minutes
// after daylight saving time begins on March 13, 2022.
      PreparedStatement pst1 =
       con.prepareStatement("INSERT INTO MYTABLE1 VALUES (?,?)");
      pst1.setString(1, "2022-03-13 02:15:00.00000");
      pst1.setString(2, "2022-03-13 02.15.00.00000");
      pst1.executeUpdate();
// Create a Calendar object and assign the same timestamp
// value that is in the table to the Calendar object.
// That timestamp value has the default time zone and
// locale for the system on which this program runs.
      Calendar cd = Calendar.getInstance();
      cd.set(2022, Calendar.MARCH, 13, 2, 15, 00);
      System.out.println("Calendar time: " + cd.getTime());
      Statement stmt2 =
       con.createStatement();
      ResultSet rs2 = stmt2.executeQuery(
       "SELECT TSTAMP1, TSTAMP2 FROM MYTABLE1");
// Retrieve the TIMESTAMP values using ResultSet.getString
// to allow the driver to prevent daylight saving time
// adjustment.
      while (rs2.next()) {
       System.out.println("TSTAMP1 (with time zone): " +
        rs2.getString(1));
       System.out.println("TSTAMP2 (without time zone): " +
        rs2.getString(2));
      }
 }
}
```

If you run the program above in Pacific Daylight Time, you receive the following results:

```
Calendar time: Sun Mar 13 03:15:00 PDT 2022
TSTAMP1 (with time zone): 2022-03-13 02:15:00.000000-07:00
TSTAMP2 (without time zone): 2022-03-13 02:15:00.000000
```

Data loss for timestamp data in JDBC and SQLJ applications

For Db2 for z/OS Version 10 or later, or Db2 on Linux, UNIX, and Windows systems Version 9.7 or later, you can specify the precision of the fractional part of a TIMESTAMP column, with a maximum precision of 12 digits. The fractional part of a Java timestamp value can have up to 9 digits of precision. Depending on the column definition, data loss can occur when you update a TIMESTAMP(*p*) column or retrieve data from a TIMESTAMP(*p*) column.

Data loss for input data

If you use a `setTimestamp` call to pass a timestamp value to a TIMESTAMP(*p*) column, the maximum precision of the Java value that is sent to the data source is 9. If you use a `setTimestamp` call to pass a timestamp value to a TIMESTAMP column at a data source that does not support TIMESTAMP(*p*), the maximum precision of the Java value that is sent to the data source is 6. For input to a TIMESTAMP(*p*) column, if the precision of the target column is less than the precision of the input value, the data source truncates the excess digits in the fractional part of the timestamp.

If you use a `setString` call to pass the input value, it is possible to send a value with a precision of greater than 9 to the data source.

For IBM Data Server Driver for JDBC and SQLJ version 3.59 or later, no data loss occurs if the TIMESTAMP(*p*) column is big enough to accommodate the input value. For IBM Data Server Driver for JDBC and SQLJ version 3.58 or earlier, data loss depends on the setting of the deferPrepares property and the sendDataAsIs property:

- If sendDataAsIs is set to `true`, the IBM Data Server Driver for JDBC and SQLJ sends the string to the data source as-is, so the fractional part of the timestamp value can be more than 9 digits. If the value of *p* in the TIMESTAMP(*p*) column is greater than or equal to the number of digits in the fractional part of the input data, no data loss occurs.
- If sendDataAsIs is set to `false`, data loss depends on the deferPrepares setting.
- If deferPrepares is set to `true`, the *first* time that an UPDATE statement is executed, the IBM Data Server Driver for JDBC and SQLJ sends the string to the data source as-is, so the fractional part of the timestamp value can be more than 9 digits. If the value of *p* in the TIMESTAMP(*p*) column is greater than or equal to the number of digits in the fractional part of the input data, no data loss occurs.

  For subsequent executions of the UPDATE statement, the IBM Data Server Driver for JDBC and SQLJ can determine that the target data type is a TIMESTAMP data type. If the data source supports TIMESTAMP(*p*) columns, the driver converts the input value to a java.sql.Timestamp value with a maximum precision of 9. If the data source does not support TIMESTAMP(*p*) columns, the driver converts the input value to a java.sql.Timestamp value with a maximum precision of 6. Data loss occurs if the original value has more precision than the converted java.sql.Timestamp value, or if the java.sql.Timestamp value has more precision than the TIMESTAMP(*p*) column.
- If deferPrepares is set to `false`, the IBM Data Server Driver for JDBC and SQLJ can determine that the target data type is a TIMESTAMP data type. If the data source supports TIMESTAMP(*p*) columns, the driver converts the input value to a java.sql.Timestamp value with a maximum precision of 9. If the data source does not support TIMESTAMP(*p*) columns, the driver converts the input value to a java.sql.Timestamp value with a maximum precision of 6. Data loss occurs if the original value has more precision than the converted java.sql.Timestamp value, or if the java.sql.Timestamp value has more precision than the TIMESTAMP(*p*) column.

You can lessen data loss for input timestamp values by using a `setString` call and setting sendDataAsIs to `true`. However, if you set sendDataAsIs to `true`, you need to ensure that application data types are compatible with data source data types.

Data loss for output data

When you use a `getTimestamp` or `getString` call to retrieve data from a TIMESTAMP(*p*) column, the IBM Data Server Driver for JDBC and SQLJ converts the value to a java.sql.Timestamp value with a maximum precision of 9. If the source value has a precision of greater than 9, the driver truncates the fractional part of the retrieved value to nine digits. If you do not want truncation to occur, in the SELECT statement that retrieves the TIMESTAMP(*p*) value, you can cast the TIMESTAMP(*p*) value to a character data type, such as VARCHAR, and use `getString` to retrieve the value from the `ResultSet`.

Retrieval of special values from DECFLOAT columns in Java applications

Special handling is necessary if you retrieve values from DECFLOAT columns, and the DECFLOAT columns contain the values NaN, Infinity, or -Infinity.

The recommended Java data type for retrieval of DECFLOAT column values is java.math.BigDecimal. However, you receive SQL error code -4231 if you perform either of these operations:

- Retrieve the value NaN, Infinity, or -Infinity from a DECFLOAT column using the JDBC `java.sql.ResultSet.getBigDecimal` or `java.sql.ResultSet.getObject` method
- Retrieve the value NaN, Infinity, or -Infinity from a DECFLOAT column into a java.math.BigDecimal variable in an SQLJ clause of an SQLJ program

You can circumvent this restriction by testing for the -4231 error, and retrieving the special value using the `java.sql.ResultSet.getDouble` or `java.sql.ResultSet.getString` method.

Suppose that the following SQL statements were used to create and populate a table.

```
CREATE TABLE TEST.DECFLOAT_TEST
(
 INT_VAL INT,
 DECFLOAT_VAL DECFLOAT
);
INSERT INTO TEST.DECFLOAT_TEST (INT_VAL, DECFLOAT_VAL) VALUES (1, 123.456),
INSERT INTO TEST.DECFLOAT_TEST (INT_VAL, DECFLOAT_VAL) VALUES (2, INFINITY),
INSERT INTO TEST.DECFLOAT_TEST (INT_VAL, DECFLOAT_VAL) VALUES (3, -123.456),
INSERT INTO TEST.DECFLOAT_TEST (INT_VAL, DECFLOAT_VAL) VALUES (4, -INFINITY),
INSERT INTO TEST.DECFLOAT_TEST (INT_VAL, DECFLOAT_VAL) VALUES (5, NaN);
```

The following code retrieves the contents of the DECFLOAT column using the `java.sql.ResultSet.getBigDecimal` method. If retrieval fails because the column value is NaN, INFINITY, or -INFINITY, the program retrieves the value using the `java.sql.ResultSet.getBigDouble` method.

```
final static int DECFLOAT_SPECIALVALUE_ENCOUNTERED = -4231;
java.sql.Connection con =
  java.sql.DriverManager.getConnection("jdbc:db2://localhost:50000/sample"
    , "userid", "password");
java.sql.Statement stmt = con.createStatement();
java.sql.ResultSet rs = stmt.executeQuery(
 "SELECT INT_VAL, DECFLOAT_VAL FROM TEST.DECFLOAT_TEST ORDER BY INT_VAL");
int i = 0;
while (rs.next()) {
 try {
  System.out.println("\nRow ” + ++i);
  System.out.println("INT_VAL      = " + rs.getInt(1));
  System.out.println("DECFLOAT_VAL = " + rs.getBigDecimal(2));
 }
 catch (java.sql.SQLException e) {
  System.out.println("Caught SQLException" + e.getMessage());
  if (e.getErrorCode() == DECFLOAT_SPECIALVALUE_ENCOUNTERED) {
  // getBigDecimal failed because the retrieved value is NaN,
  // INFINITY, or -INFINITY, so retry with getDouble.
     double d = rs.getDouble(2);
     if (d == Double.POSITIVE_INFINITY) {
       System.out.println("DECFLOAT_VAL = +INFINITY");
     } else if (d == Double.NEGATIVE_INFINITY) {
       System.out.println("DECFLOAT_VAL = -INFINITY");
     } else if (d == Double.NaN) {
       System.out.println("DECFLOAT_VAL = NaN");
     } else {
       System.out.println("DECFLOAT_VAL = " + d);
     }
  } else {
     e.printStackTrace();
    }
 }
```

The following code retrieves the contents of the DECFLOAT column using the `java.sql.ResultSet.getBigDecimal` method. If retrieval fails because the column value is NaN, INFINITY, or -INFINITY, the program retrieves the value using the `java.sql.ResultSet.getString` method.

```
final static int DECFLOAT_SPECIALVALUE_ENCOUNTERED = -4231;
java.sql.Connection con =
  java.sql.DriverManager.getConnection("jdbc:db2://localhost:50000/sample"
    , "userid", "password");
java.sql.Statement stmt = con.createStatement();
java.sql.ResultSet rs = stmt.executeQuery(
 "SELECT INT_VAL, DECFLOAT_VAL FROM TEST.DECFLOAT_TEST ORDER BY INT_VAL");
int i = 0;
while (rs.next()) {
 try {
  System.out.println("\nRow ” + ++i);
  System.out.println("INT_VAL      = " + rs.getInt(1));
  System.out.println("DECFLOAT_VAL = " + rs.getBigDecimal(2));
 }
 catch (java.sql.SQLException e) {
```

```
  System.out.println("Caught SQLException" + e.getMessage());
  if (e.getErrorCode() == DECFLOAT_SPECIALVALUE_ENCOUNTERED) {
  // getBigDecimal failed because the retrieved value is NaN,
  // INFINITY, or -INFINITY, so retry with getString.
     System.out.println("DECFLOAT_VAL = "+rs.getString(2));
  } else {
     e.printStackTrace();
    }
 }
```

Use of PreparedStatement.setTimestamp to set values in TIMESTAMP WITH TIME ZONE columns

When you use `PreparedStatement.setTimestamp` to set a value in a TIMESTAMP WITH TIME ZONE column, you should specify a `com.ibm.db2.jcc.DBTimestamp` object for the input value.

Use of a `com.ibm.db2.jcc.DBTimestamp` object ensures that the correct time zone is assigned to the target column.

In certain cases, the target data type for a table update is not known. Possible reasons are:

- The deferPrepares and sendDataAsIs properties are set so that the target data type is not known.
- The input parameter is for a CALL statement, and the stored procedure is on a Db2 for z/OS data server.

If the target data type is not known, the IBM Data Server Driver for JDBC and SQLJ must choose a target data type. When an input parameter has type `com.ibm.db2.jcc.DBTimestamp`, and the target data server supports TIMESTAMP WITH TIME ZONE, the driver always chooses TIMESTAMP with TIMEZONE as the target data type.

Before version 3.63 or 4.13 of the IBM Data Server Driver for JDBC and SQLJ, if the target data type is not known, the target data server supports TIMESTAMP WITH TIME ZONE, and the input data type is `java.sql.Timestamp`, the driver chooses TIMESTAMP WITH TIME ZONE as the target type.

Starting with version 3.63 or 4.13, if the target data type is not known, the target data server supports TIMESTAMP WITH TIME ZONE, and the input data type is `java.sql.Timestamp`, the driver chooses TIMESTAMP WITH TIME ZONE as the target type, except when the input object has a value of 0001-01-01-00:00:00.000000 or 9999-12-31-23:59:59.999999. In those cases, the driver chooses the TIMESTAMP type, without a time zone. Use of the TIMESTAMP data type in those two cases prevents an overflow condition from occurring because of adjustment of the value for the implied time zone. The implied time zone is the time zone of the Java virtual machine (JVM). Starting with version 3.65 or 4.15, the timestamps for which the driver chooses the TIMESTAMP type, without the time zone, are 0001-01-01, with any time, or 9999-12-31, with any time.

Migration consideration

TIMESTAMP WITH TIME ZONE is first supported in Db2 for z/OS Version 10 new-function mode. Before Version 10 new-function mode, if the value that is assigned to a column (the second parameter of `PreparedStatement.setTimestamp`) has the `java.sql.Timestamp` data type, and the column data type is not known, the IBM Data Server Driver for JDBC and SQLJ chooses TIMESTAMP as the column data type. However, starting with Db2 for z/OS Version 10 new-function mode, unless the value that is assigned to the column is 0001-01-01-00:00:00.000000 or 9999-12-31-23:59:59.999999, the driver chooses TIMESTAMP WITH TIME ZONE as the column data type. If the driver chooses the TIMESTAMP data type, and the column type is actually TIMESTAMP WITH TIME ZONE, the database manager sets the time zone in the target column using the value of the IMPLICIT_TIMEZONE DECP value. This value might differ from the value that is inserted prior to Version 10 new-function mode.

To produce the same results before and after new-function mode when `PreparedStatement.setTimestamp` is executed, specify a `com.ibm.db2.jcc.DBTimestamp` value as the second parameter.

Properties for the IBM Data Server Driver for JDBC and SQLJ

IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

IBM Data Server Driver for JDBC and SQLJ property names are case-sensitive.

Methods for setting the properties

Properties can be set in one of the following ways:

- Using `setXXX` methods, where XXX is the unqualified property name, with the first character capitalized.

  Properties are applicable to the following IBM Data Server Driver for JDBC and SQLJ-specific implementations that inherit from `com.ibm.db2.jcc.DB2BaseDataSource`:

  - `com.ibm.db2.jcc.DB2SimpleDataSource`
  - `com.ibm.db2.jcc.DB2ConnectionPoolDataSource`
  - `com.ibm.db2.jcc.DB2XADataSource`
- In a `java.util.Properties` value in the *info* parameter of a `DriverManager.getConnection` call.
- In a `java.lang.String` value in the *url* parameter of a DriverManager.getConnection call.

  If you specify a property name that does not exist, the IBM Data Server Driver for JDBC and SQLJ does nothing with the property setting, and does not issue an error.

  Some properties with an int data type have predefined constant field values. You must resolve constant field values to their integer values before you can use those values in the *url* parameter. For example, you cannot use com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL in a *url* parameter. However, you can build a URL string that includes com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL, and assign the URL string to a String variable. Then you can use the String variable in the *url* parameter:

```
String url =
 "jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1" +
 ":user=dbadm;password=dbadm;" +
 "traceLevel=" +
 (com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL) + ";";

 Connection con =
   java.sql.DriverManager.getConnection(url);
```

Priorities of property settings

If a property is set by multiple methods, the following priority rules apply to the settings:

- If a db2.jcc.override.*property* global configuration property is set in the IBM Data Server Driver for JDBC and SQLJ configuration properties file, that setting has the highest priority, and overrides all other settings.
- If *property* is set on a `DataSource` or `Connection` instance, it has the next highest priority. Settings on a `DataSource` or `Connection` instance have equal priority with each other.
- Global configuration property db2.jcc.*property* is set when the driver is loaded, and has the lowest priority.

Examples of setting a property

To set property `sslKeyStoreLocation`, use one of the following methods:

- Set the property on a `DataSource` instance.

Suppose that ds is defined as a DataSource instance, and String variable ksloc contains the keystore location. You can set the keystore location on the ds instance like this:

```
ds.setSslKeyStoreLocation(ksloc);
```

- Set the property on a Connection instance.

  Suppose that con is defined as a Connection instance, String variable url is the Connection URL, and you want to set the keystore location to /a/b/c. You can set the keystore location and create the Connection instance like this:

```
String url =
     "jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1" +
     ":user=dbadm;password=dbadm;" +
     "sslKeyStoreLocation=" +
     "/a/b/c" +
     ";";

     Connection con = java.sql.DriverManager.getConnection(url);
```

- Set the property in the IBM Data Server Driver for JDBC and SQLJ configuration properties file.

  You can set the property like this, to override all other settings of sslKeyStoreLocation:

```
db2.jcc.override.sslKeyStoreLocation=/a/b/c
```

  Alternatively, you can set the property so that all other settings of sslKeyStoreLocation override it:

```
db2.jcc.sslKeyStoreLocation=/a/b/c
```

Related concepts

“IBM Data Server Driver for JDBC and SQLJ support for SSL” on page 579
The IBM Data Server Driver for JDBC and SQLJ provides support for the Secure Sockets Layer (SSL) through the Java Secure Socket Extension (JSSE).

Related tasks

“Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ” on page 13
A JDBC application can establish a connection to a data source using the JDBC DriverManager interface, which is part of the java.sql package.

“Connecting to a data source using the DataSource interface” on page 20
If your applications need to be portable among data sources, you should use the DataSource interface.

Related reference

“IBM Data Server Driver for JDBC and SQLJ configuration properties” on page 288
The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products

Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Unless otherwise noted, all properties are in com.ibm.db2.jcc.DB2BaseDataSource.

Those properties are:

affinityFailbackInterval
Specifies the length of the interval, in seconds, that the IBM Data Server Driver for JDBC and SQLJ waits between attempts to fail back an existing connection to the primary server. A value that is less than or equal to 0 means that the connection does not fail back. The default is DB2BaseDataSource.NOT_SET (0).

Attempts to fail back connections to the primary server are made at transaction boundaries after the specified interval elapses.

affinityFailbackInterval is used only if the values of properties enableSeamlessFailover and enableClientAffinitiesList are DB2BaseDataSource.YES (1).

affinityFailbackInterval applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

allowNextOnExhaustedResultSet
Specifies how the IBM Data Server Driver for JDBC and SQLJ handles a ResultSet.next() call for a forward-only cursor that is positioned after the last row of the ResultSet. The data type of this property is int.

Possible values are:

DB2BaseDataSource.YES (1)
For a ResultSet that is defined as TYPE_FORWARD_ONLY, ResultSet.next() returns false if the cursor was previously positioned after the last row of the ResultSet. ResultSet.next() returns false, regardless of whether the cursor is open or closed.

DB2BaseDataSource.NO (2)
For a ResultSet that is defined as TYPE_FORWARD_ONLY, when ResultSet.next() is called, and the cursor was previously positioned after the last row of the ResultSet, the driver throws a java.sql.SQLException with error text "Invalid operation: result set is closed." This value is the default.

allowNullResultSetForExecuteQuery
Specifies whether the IBM Data Server Driver for JDBC and SQLJ returns null when Statement.executeQuery, PreparedStatement.executeQuery, or CallableStatement.executeQuery is used to execute a CALL statement for a stored procedure that does not return any result sets.

Possible values are:

DB2BaseDataSource.NOT_SET (0)
The behavior is the same as for DB2BaseDataSource.NO.

DB2BaseDataSource.YES (1)
The IBM Data Server Driver for JDBC and SQLJ returns null when Statement.executeQuery, PreparedStatement.executeQuery, or CallableStatement.executeQuery is used to execute a CALL statement for a stored procedure that does not return any result sets. This behavior does not conform to the JDBC standard.

DB2BaseDataSource.NO (2)
The IBM Data Server Driver for JDBC and SQLJ throws an SQLException when Statement.executeQuery, PreparedStatement.executeQuery, or CallableStatement.executeQuery is used to execute a CALL statement for a stored procedure that does not return any result sets. This behavior conforms to the JDBC standard.

atomicMultiRowInsert
Specifies whether batch operations that use PreparedStatement methods to modify a table are atomic or non-atomic. The data type of this property is int.

For connections to Db2 for z/OS, this property applies only to batch INSERT operations.

For connections to Db2 on Linux, UNIX, and Windows systems or IBM Informix, this property applies to batch INSERT, MERGE, UPDATE, or DELETE operations.

Possible values are:

DB2BaseDataSource.YES (1)
Batch operations are atomic. Insertion of all rows in the batch is considered to be a single operation. If insertion of a single row fails, the entire operation fails with a BatchUpdateException. Use of a batch statement that returns auto-generated keys fails with a BatchUpdateException.

If atomicMultiRowInsert is set to DB2BaseDataSource.YES (1):

- If the target data source is Db2 for z/OS the following operations are not allowed:
  - Insertion of more than 32767 rows in a batch results in a `BatchUpdateException`.
  - Calling more than one of the following methods against the same parameter in different rows results in a `BatchUpdateException`:
    - `PreparedStatement.setAsciiStream`
    - `PreparedStatement.setCharacterStream`
    - `PreparedStatement.setUnicodeStream`

DB2BaseDataSource.NO (2)
Batch inserts are non-atomic. Insertion of each row is considered to be a separate execution. Information on the success of each insert operation is provided by the `int[]` array that is returned by `Statement.executeBatch`.

DB2BaseDataSource.NOT_SET (0)
Batch inserts are non-atomic. Insertion of each row is considered to be a separate execution. Information on the success of each insert operation is provided by the `int[]` array that is returned by `Statement.executeBatch`. This value is the default.

autocommit
Sets the default autocommit value for a Connection or DataSource instance. All connections that are derived from a DataSource inherit the autocommit property set on the DataSource.

blockingReadConnectionTimeout
The amount of time in seconds before a connection socket read times out. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, and affects all requests that are sent to the data source after a connection is successfully established. The default is 0. A value of 0 means that there is no timeout.

clientBidiStringType

Used if enableBidiLayoutTransformation is enabled. Specifies the string type that is used by the client application. Possible values for the property and their corresponding text attributes are specified in the following table:

Table 35. String type values and corresponding attributes for the clientBidiStringType and serverBidiStringType properties

		Text Attributes				
String type value integer constant	**String type value**	**Type of text**	**Orientation**	**Symmetric swapping**	**Numeral shape**	**Text shapes**
4	`DB2BaseDataSource.BIDI_ST4`	Visual	Left-to-right	No	Nominal	Shaped
5	`DB2BaseDataSource.BIDI_ST5`	Implicit	Left-to-right	Yes	Nominal	Nominal
6	`DB2BaseDataSource.BIDI_ST6`	Implicit	Right-to-left	Yes	Nominal	Nominal

Table 35. String type values and corresponding attributes for the clientBidiStringType and serverBidiStringType properties (continued)

		Text Attributes				
String type value integer constant	**String type value**	**Type of text**	**Orientation**	**Symmetric swapping**	**Numeral shape**	**Text shapes**
7	`DB2BaseDataSource.BIDI_ST7`	Visual	Right-to-left	No	Nominal	Shaped
8	`DB2BaseDataSource.BIDI_ST8`	Visual	Right-to-left	No	Nominal	Shaped
9	`DB2BaseDataSource.BIDI_ST9`	Implicit	Right-to-left	Yes	Nominal	Shaped
10	`DB2BaseDataSource.BIDI_ST10`	Implicit	Contextual left-to-right	Yes	Nominal	Nominal
11	`DB2BaseDataSource.BIDI_ST11`	Implicit	Contextual right-to-left	Yes	Nominal	Nominal

clientDebugInfo
Specifies a value for the CLIENT DEBUGINFO connection attribute to notify the data server that stored procedures and user-defined functions that are using the connection are running in debug mode. CLIENT DEBUGINFO is used by the Db2 Unified Debugger. The data type of this property is String. The maximum length is 254 bytes.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

clientRerouteAlternateServerName
Specifies one or more server names for client reroute. The data type of this property is String.

When `enableClientAffinitiesList=DB2BaseDataSource.YES` (1), clientRerouteAlternateServerName must contain the name of the primary server as well as alternate server names. The server that is identified by serverName and portNumber is the primary server. That server name must appear at the beginning of the clientRerouteAlternateServerName list.

If more than one server name is specified, delimit the server names with commas (,) or spaces. The number of values that is specified for clientRerouteAlternateServerName must match the number of values that is specified for clientRerouteAlternatePortNumber.

clientRerouteAlternateServerName applies to:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to all supported database products
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 on Linux, UNIX, and Windows systems

clientRerouteAlternatePortNumber
Specifies one or more port numbers for client reroute. The data type of this property is String.

When `enableClientAffinitiesList=DB2BaseDataSource.YES` (1), clientRerouteAlternatePortNumber must contain the port number for the primary server as well as port numbers for alternate servers. The server that is identified by serverName and portNumber is the primary server. That port number must appear at the beginning of the clientRerouteAlternatePortNumber list.

If more than one port number is specified, delimit the port numbers with commas (,) or spaces. The number of values that is specified for clientRerouteAlternatePortNumber must match the number of values that is specified for clientRerouteAlternateServerName.

clientRerouteAlternatePortNumber applies to:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to all supported database products
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 on Linux, UNIX, and Windows systems

clientRerouteServerListJNDIName
Identifies a JNDI reference to a `DB2ClientRerouteServerList` instance in a JNDI repository of reroute server information. clientRerouteServerListJNDIName applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, and to connections that are established through the `DataSource` interface.

If the value of clientRerouteServerListJNDIName is not null, clientRerouteServerListJNDIName provides the following functions:

- Allows information about reroute servers to persist across JVMs
- Provides an alternate server location if the first connection to the data source fails

clientRerouteServerListJNDIContext
Specifies the JNDI context that is used for binding and lookup of the `DB2ClientRerouteServerList` instance. clientRerouteServerListJNDIContext applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, and to connections that are established through the `DataSource` interface.

If clientRerouteServerListJNDIContext is not set, the IBM Data Server Driver for JDBC and SQLJ creates an initial context by using system properties or the jndi.properties file.

clientRerouteServerListJNDIContext can be set **only** by using the following method:

```
public void setClientRerouteServerListJNDIContext(javax.naming.Context registry)
```

commandTimeout
Specifies the maximum time in seconds that an application that runs under the IBM Data Server Driver for JDBC and SQLJ waits for SQL operations to complete before the driver throws an `SQLException`. The wait time includes time to obtain a transport, perform failover if needed, send the request, and wait for a response. The data type of this parameter is int. The default is 0, which means that there is no timeout.

If the `java.sql.Statement.setQueryTimeout` method is invoked, the query timeout value that is set through `Statement.setQueryTimeout` overrides the commandTimeout value.

commandTimeout applies to the execution of `Statement`, `PreparedStatement`, and `CallableStatement` methods `execute`, `executeQuery`, and `executeUpdate`. commandTimeout also applies to the `executeBatch` method if property queryTimeoutInterruptProcessingMode has the value INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET (2).

The SQL error code that is returned with the `SQLException` depends on the data server and the value of property queryTimeoutInterruptProcessingMode:

- For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS data servers, the queryTimeoutInterruptProcessingMode value is always INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET (2).
  - If sysplex workload balancing is enabled, SQL error code -30108 is returned.
  - If automatic client reroute processing is enabled, and sysplex workload balancing is disabled, SQL error code -4498 is returned.
  - If neither sysplex workload balancing nor automatic client reroute processing is enabled, SQL error code -4499 is returned.

  Automatic client reroute processing is not initiated if the commandTimeout value is exceeded.
- For connections to other data servers:
  - If the queryTimeoutInterruptProcessingMode value is INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL (1), -952 is returned.
  - If the queryTimeoutInterruptProcessingMode value is INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET (2):
    - If Db2 workload balancing is enabled, SQL error -30108 is returned.
    - If automatic client reroute processing is enabled, and Db2 workload is disabled, SQL error -4498 is returned.
    - If neither automatic client reroute processing nor Db2 workload is enabled, SQL error -4498 is returned.

If configuration property db2.jcc.enableInetAddressGetHostName is set to `true`, the following situations might occur:

- Actual wait times might exceed the commandTimeout value. This situation can occur when the driver needs to do several DNS lookup operations to resolve IP addresses to host names. The amount by which the wait time exceeds the commandTimeout value depends on the number of DNS lookup operations, and the amount of time that each DNS lookup operation takes.
- The extra time that is required for DNS lookup operations might cause more timeout conditions than if db2.jcc.enableInetAddressGetHostName is set to `false`.

connectionCloseWithInFlightTransaction
Specifies whether the IBM Data Server Driver for JDBC and SQLJ throws an `SQLException` or rolls back a transaction without throwing an `SQLException` when a connection is closed in the middle of the transaction. Possible values are:

DB2BaseDataSource.NOT_SET (0)
The behavior is the same as for DB2BaseDataSource.CONNECTION_CLOSE_WITH_EXCEPTION.

DB2BaseDataSource.CONNECTION_CLOSE_WITH_EXCEPTION (1)
When a connection is closed in the middle of a transaction, an `SQLException` with error -4471 is thrown.

DB2BaseDataSource.CONNECTION_CLOSE_WITH_ROLLBACK (2)
When a connection is closed in the middle of a transaction, the transaction is rolled back, and no `SQLException` is thrown.

DB2BaseDataSource.CONNECTION_CLOSE_WITH_COMMIT (3)
When a connection is closed in the middle of a transaction, the transaction is committed, and no `SQLException` is thrown. Use this option only when migrating applications to Db2.

connectionTimeout
Specifies the maximum time in seconds that the IBM Data Server Driver for JDBC and SQLJ waits for a reply from a group of data servers when the driver attempts to establish a connection. If the driver does not receive a reply after the amount of time that is specified by connectionTimeout, the driver throws an `SQLException` with SQL error code -4499. The data type of this parameter is int. The default value is 0.

If connectionTimeout is set to a positive value, that value overrides any other timeout values that are set on a connection, such as loginTimeout. A connection is attempted to the member of the group of data servers with the greatest load capacity. If none of the members are up, a connection is attempted to the group IP address that is specified on the `DataSource`. If the connection cannot be established with any of the data servers within the amount of time that is specified by connectionTimeout, an `SQLException` is thrown.

If connectionTimeout is set to 0, and automatic client reroute is not enabled, there is no time limit.

If connectionTimeout is set to 0, and automatic client reroute is enabled against a Db2 for z/OS data sharing group, Db2 pureScale® instance, or IBM Informix high availability cluster, automatic client reroute properties such as maxRetriesForClientReroute and retryIntervalForClientReroute control the amount of time that is needed to establish the connection.

If configuration property db2.jcc.enableInetAddressGetHostName is set to `true`, the following situations might occur:

- Actual wait times might exceed the connectionTimeout value. This situation can occur when the driver needs to do several DNS lookup operations to resolve IP addresses to host names. The amount by which the wait time exceeds the connectionTimeout value depends on the number of DNS lookup operations, and the amount of time that each DNS lookup operation takes.
- The extra time that is required for DNS lookup operations might cause more timeout conditions than if db2.jcc.enableInetAddressGetHostName is set to `false`.

databaseName
Specifies the name for the data source. This name is used as the *database* portion of the connection URL. The name depends on whether IBM Data Server Driver for JDBC and SQLJ type 4 connectivity or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity is used.

For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity:

- If the connection is to a Db2 for z/OS server, the databaseName value is the Db2 location name that is defined during installation. All characters in this value must be uppercase characters. You can determine the location name by executing the following SQL statement on the server:

```
SELECT CURRENT SERVER FROM SYSIBM.SYSDUMMY1;
```

- If the connection is to a Db2 on Linux, UNIX, and Windows systems server, the databaseName value is the database name that is defined during installation.
- If the connection is to an IBM Informix server, *database* is the database name. The name is case-insensitive. The server converts the name to lowercase.
- If the connection is to an IBM Cloudscape server, the databaseName value is the fully qualified name of the file that contains the database. This name must be enclosed in double quotation marks ("). For example:

```
"c:/databases/testdb"
```

If this property is not set, connections are made to the local site.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity:

- The databaseName value is the location name for the data source. The location name is defined in the SYSIBM.LOCATIONS catalog table.

  If the databaseName property is not set, the connection location depends on the type of environment in which the connection is made. If the connection is made in an environment such as a stored procedure, CICS, or IMS environment, where a Db2 connection to a location is previously established, that connection is used. The connection URL for this case is jdbc:default:connection. If a connection to Db2 is not previously established, the connection is to the local site. The connection URL for this case is jdbc:db2os390: or jdbc:db2os390sqlj.

decimalSeparator
Specifies the decimal separator for input and output, for decimal, floating point, or decimal floating-point data values. The data type of this property is int.

If the value of the sendDataAsIs property is `true`, decimalSeparator affects only output values.

Possible values are:

DB2BaseDataSource.DECIMAL_SEPARATOR_NOT_SET (0)
A period is used as the decimal separator. This value is the default.

DB2BaseDataSource.DECIMAL_SEPARATOR_PERIOD (1)
A period is used as the decimal separator.

DB2BaseDataSource.DECIMAL_SEPARATOR_COMMA (2)
A comma is used as the decimal separator.

When DECIMAL_SEPARATOR_COMMA is set, the result of `ResultSet.getString` on a decimal, floating point, or decimal floating-point value has a comma as a separator. However, if the `toString` method is executed on a value that is retrieved with a `ResultSet.getXXX` method that returns a decimal, floating point, or decimal floating-point value, the result has a decimal point as the decimal separator.

decimalStringFormat
Specifies the string format for data that is retrieved from a DECIMAL or DECFLOAT column when the SDK for Java is Version 1.5 or later. The data type of this property is int. Possible values are:

DB2BaseDataSource.DECIMAL_STRING_FORMAT_NOT_SET (0)
The IBM Data Server Driver for JDBC and SQLJ returns decimal values in the format that the `java.math.BigDecimal.toString` method returns them. This value is the default.

For example, the value 0.0000000004 is returned as 4E-10.

DB2BaseDataSource.DECIMAL_STRING_FORMAT_TO_STRING (1)
The IBM Data Server Driver for JDBC and SQLJ returns decimal values in the format that the `java.math.BigDecimal.toString` method returns them.

For example, the value 0.0000000004 is returned as 4E-10.

DB2BaseDataSource.DECIMAL_STRING_FORMAT_TO_PLAIN_STRING (2)
The IBM Data Server Driver for JDBC and SQLJ returns decimal values in the format that the `java.math.BigDecimal.toPlainString` method returns them.

For example, the value 0.0000000004 is returned as 0.0000000004.

This property has no effect for earlier versions of the SDK for Java. For those versions, the IBM Data Server Driver for JDBC and SQLJ returns decimal values in the format that the `java.math.BigDecimal.toString` method returns them.

defaultIsolationLevel
Specifies the default transaction isolation level for new connections. The data type of this property is int. When defaultIsolationLevel is set on a `DataSource`, all connections that are created from that `DataSource` have the default isolation level that is specified by defaultIsolationLevel.

For Db2 data sources, the default is `java.sql.Connection.TRANSACTION_READ_COMMITTED`.

For IBM Informix databases, the default depends on the type of data source. The following table shows the defaults.

Table 36. Default isolation levels for IBM Informix databases

Type of data source	Default isolation level
ANSI-compliant database with logging	java.sql.Connection.TRANSACTION_SERIALIZABLE
Database without logging	java.sql.Connection.TRANSACTION_READ_UNCOMMITTED

Table 36. Default isolation levels for IBM Informix databases (continued)

Type of data source	Default isolation level
Non-ANSI-compliant database with logging	java.sql.Connection.TRANSACTION_READ_COMMITTED

deferPrepares
Specifies whether invocation of the `Connection.prepareStatement` method results in immediate preparation of an SQL statement on the data source, or whether statement preparation is deferred until the `PreparedStatement.execute` method is executed. The data type of this property is boolean.

deferPrepares is supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 on Linux, UNIX, and Windows systems, and for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

Possible values are:

true
Statement preparation on the data source does not occur until the `PreparedStatement.execute` method is executed. This value is the default.

false
Statement preparation on the data source occurs when the `Connection.prepareStatement` method is executed.

Deferring prepare operations can reduce network delays. However, if you defer prepare operations, you need to ensure that input data types match table column types.

description
A description of the data source. The data type of this property is String.

downgradeHoldCursorsUnderXa
Specifies whether cursors that are defined WITH HOLD can be opened under XA connections.

downgradeHoldCursorsUnderXa applies to:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS servers.
- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 on Linux, UNIX, and Windows systems servers.

The default is `false`, which means that a cursor that is defined WITH HOLD cannot be opened under an XA connection. An exception is thrown when an attempt is made to open that cursor.

If downgradeHoldCursorsUnderXa is set to `true`, a cursor that is defined WITH HOLD can be opened under an XA connection. However, the cursor has the following restrictions:

- When the cursor is opened under an XA connection, the cursor does not have WITH HOLD behavior. The cursor is closed at XA End.
- A cursor that is open before XA Start on a local transaction is closed at XA Start.

driverType
For the `DataSource` interface, determines which driver to use for connections. The data type of this property is int. Valid values are 2 or 4. 2 is the default.

enableClientAffinitiesList
Specifies whether the IBM Data Server Driver for JDBC and SQLJ enables client affinities for cascaded failover support. The data type of this property is int. Possible values are:

`DB2BaseDataSource.YES` (1)
The IBM Data Server Driver for JDBC and SQLJ enables client affinities for cascaded failover support. Therefore, only servers that are specified in the clientRerouteAlternateServerName and clientRerouteAlternatePortNumber properties are retried. The driver does not attempt to reconnect to any other servers.

For example, suppose that clientRerouteAlternateServerName contains the following string:

```
host1,host2,host3
```

Also suppose that clientRerouteAlternatePortNumber contains the following string:

```
port1,port2,port3
```

When client affinities are enabled, the retry order is:

1. host1:port1
2. host2:port2
3. host3:port3

DB2BaseDataSource.NO (2)
The IBM Data Server Driver for JDBC and SQLJ does not enable client affinities for cascaded failover support.

DB2BaseDataSource.NOT_SET (0)
The IBM Data Server Driver for JDBC and SQLJ does not enable client affinities for cascaded failover support. This value is the default.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

enableNamedParameterMarkers
Specifies whether support for named parameter markers is enabled in the IBM Data Server Driver for JDBC and SQLJ. The data type of this property is int. Possible values are:

DB2BaseDataSource.YES (1)
Named parameter marker support is enabled in the IBM Data Server Driver for JDBC and SQLJ.

DB2BaseDataSource.NO (2)
Named parameter marker support is not enabled in the IBM Data Server Driver for JDBC and SQLJ.

The driver sends an SQL statement with named parameter markers to the target data source without modification. The success or failure of the statement depends on a number of factors, including the following ones:

- Whether the target data source supports named parameter markers.
- Whether the deferPrepares property value is `true` or `false`.
- Whether the sendDataAsIs property value is `true` or `false`.

Recommendation: To avoid unexpected behavior in an application that uses named parameter markers, set enableNamedParameterMarkers to YES.

DB2BaseDataSource.NOT_SET (0)
The behavior is the same as the behavior for `DB2BaseDataSource.NO` (2). This value is the default.

enableBidiLayoutTransformation

Specifies whether the driver needs to perform BiDi (bidirectional) Layout transformation on SQL statements, input parameters, or data received from the database. The data type of this property is boolean and the default value is `false`.

enableSeamlessFailover
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses seamless failover for client reroute. The data type of this property is int.

For connections to Db2 for z/OS, if enableSysplexWLB is set to `true`, enableSeamlessFailover has no effect. The IBM Data Server Driver for JDBC and SQLJ uses seamless failover regardless of the enableSeamlessFailover setting.

Possible values of enableSeamlessFailover are:

DB2BaseDataSource.YES (1)
The IBM Data Server Driver for JDBC and SQLJ uses seamless failover. Therefore, the driver does not throw an SQLException with SQL error code -4498, after a failed connection is reestablished, if the following conditions are true:

- The connection was not being used for a transaction at the time the failure occurred.
- There are no outstanding global resources, such as global temporary tables or open, held cursors, or connection states that prevent a seamless failover to another server.

When seamless failover occurs after the connection to a new data source is established, the driver reissues the SQL statement that was being processed when the original connection failed.

Recommendation: Set the queryCloseImplicit property to DB2BaseDataSource.QUERY_CLOSE_IMPLICIT_NO (2) when you set enableSeamlessFailover to DB2BaseDataSource.YES, if the application uses held cursors.

DB2BaseDataSource.NO (2)
The IBM Data Server Driver for JDBC and SQLJ does not use seamless failover.

When this setting is in effect, if a server goes down, the driver tries to fail back or fail over to an alternate server. If failover or failback is successful, the driver throws an SQLException with SQL error code -4498, which indicates that a connection failed but was successfully reestablished. An SQLException with SQL error code -4498 informs the application that it must retry the transaction during which the connection failure occurred. If the driver cannot reestablish a connection, it throws an SQLException with SQL error code -4499.

DB2BaseDataSource.NOT_SET (0)
The IBM Data Server Driver for JDBC and SQLJ does not use seamless failover. This value is the default.

enableSysplexWLB
Indicates whether the sysplex workload balancing function of the IBM Data Server Driver for JDBC and SQLJ is enabled. The data type of enableSysplexWLB is boolean. The default is false.

enableSysplexWLB is supported only for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

For connections to Db2 on Linux, UNIX, and Windows systems, enableSysplexWLB can have a value of true only if the servers are in a pureScale environment. For other supported database products, enableSysplexWLB can have a value of true only if the servers have sysplex workload balancing enabled.

fetchSize
Specifies the default fetch size for ResultSet objects that are generated from Statement objects. The data type of this property is int.

The fetchSize default can be overridden by the Statement.setFetchSize method. The fetchSize property does not affect Statement objects that exist when fetchSize is set.

Possible values of fetchSize are:

0 or *positive-integer*
The default *fetchSize* value for newly created Statement objects. If the fetchSize property value is invalid, the IBM Data Server Driver for JDBC and SQLJ sets the default *fetchSize* value to 0.

DB2BaseDataSource.FETCHSIZE_NOT_SET (-1)
Indicates that the default *fetchSize* value for Statement objects is 0. This value is the property default.

The fetchSize property differs from the queryDataSize property. fetchSize affects the number of rows that are returned, and queryDataSize affects the number of bytes that are returned.

fullyMaterializeLobData
Indicates whether the driver retrieves LOB locators for FETCH operations. The data type of this property is boolean.

The effect of fullyMaterializeLobData depends on whether the data source supports progressive streaming, which is also known as dynamic data format:

- If the data source does not support progressive streaming:

  If the value of fullyMaterializeLobData is `true`, LOB data is fully materialized within the JDBC driver when a row is fetched. If the value is `false`, LOB data is streamed. The driver uses locators internally to retrieve LOB data in chunks as needed. It is highly recommended that you set this value to `false` when you retrieve LOBs that contain large amounts of data. The default is `true`.

- If the data source supports progressive streaming:

  The JDBC driver ignores the value of fullyMaterializeLobData if the progressiveStreaming property is set to `DB2BaseDataSource.YES` or `DB2BaseDataSource.NOT_SET`.

This property has no effect on stored procedure parameters or on LOBs that are fetched by using scrollable cursors. LOB stored procedure parameters are always fully materialized. LOBs that are fetched by using scrollable cursors use LOB locators if progressive streaming is not in effect.

implicitRollbackOption
Specifies the actions that the IBM Data Server Driver for JDBC and SQLJ takes when a transaction encounters a deadlock or a timeout. Possible values are:

`DB2BaseDataSource.IMPLICIT_ROLLBACK_OPTION_NOT_CLOSE_CONNECTION` (1)
The IBM Data Server Driver for JDBC and SQLJ throws an `SQLException` with an SQL error code that indicates that a deadlock or timeout occurred. The SQL error code is the SQL error code that is generated by the data server after a deadlock or timeout. The driver does not close the connection.

`DB2BaseDataSource.IMPLICIT_ROLLBACK_OPTION_CLOSE_CONNECTION` (2)
The IBM Data Server Driver for JDBC and SQLJ throws a `DisconnectException` with SQL error code -4499 when a deadlock or timeout occurs. The driver closes the connection. If automatic client reroute or sysplex workload balancing is enabled, the driver disables automatic failover behavior.

`DB2BaseDataSource.IMPLICIT_ROLLBACK_OPTION_NOT_SET` (0)
This value is the default. The IBM Data Server Driver for JDBC and SQLJ throws an `SQLException` with an SQL error code that indicates that a deadlock or timeout occurred. The SQL error code is the SQL error code that is generated by the data server after a deadlock or timeout. The driver does not close the connection.

interruptProcessingMode
Specifies the behavior of the IBM Data Server Driver for JDBC and SQLJ when an application executes the `Statement.cancel` method. Possible values are:

`DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_DISABLED` (0)
Interrupt processing is disabled. When an application executes `Statement.cancel`, the IBM Data Server Driver for JDBC and SQLJ does nothing.

`DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL` (1)
When an application executes `Statement.cancel`, the IBM Data Server Driver for JDBC and SQLJ cancels the currently executing statement, if the data server supports interrupt processing. If the data server does not support interrupt processing, the IBM Data Server Driver for JDBC and SQLJ throws an `SQLException` that indicates that the feature is not supported. INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL is the default.

`DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET` (2)
When an application executes `Statement.cancel`, the IBM Data Server Driver for JDBC and SQLJ drops the underlying socket. The connection is not closed and can be reused to resubmit the statement. When the connection is reused, the driver obtains a new socket.

For connections to Db2 for z/OS data servers, the IBM Data Server Driver for JDBC and SQLJ always uses this value, regardless of the value that is specified.

If interruptProcessingMode is set to `DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL` or

DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET, and Statement.cancel is executed while an application is executing a method on a ResultSet object, the operation on the ResultSet object might not be canceled. When the Statement.cancel statement is executed, if the underlying processing for the ResultSet method is in the data server, execution of the operation is canceled. If the underlying processing for the ResultSet method is in the driver, execution of the operation is not canceled.

keepAliveTimeOut
The maximum time in seconds before each TCP KeepAlive signal is sent to the data server. The data type of this property is int. The default is 15 seconds.

IBM Data Server Driver for JDBC and SQLJ type 4 connectivity uses the TCP/IP protocol to communicate with data servers. To prevent potential failover issues that are caused by timeouts within the TCP/IP layer, it is necessary to adjust the TCP/IP KeepAlive parameters on the client. Decreasing the KeepAlive values on the client improves timely detection of server failures.

A value of 0 means that the timeout value is the default system timeout value.

keepAliveTimeOut is supported only for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

keepAliveTimeOut is not supported if the Java runtime environment is Java SE 9 or later.

loginTimeout
The maximum time in seconds to wait for a connection to a data source. After the number of seconds that are specified by loginTimeout have elapsed, the driver closes the connection to the data source. The data type of this property is int. The default is 0. A value of 0 means that the timeout value is the default system timeout value. This property is not supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

If the data server environment is a Db2 pureScale environment, the wait time for a connection is determined by a combination of loginTimeout, maxRetriesForClientReroute, and retryIntervalForClientReroute. loginTimeout determines only the time for a single attempt to establish a connection to a data server. There might be multiple attempts to establish a connection, based on the maxRetriesForClientReroute value. There might also be gaps between attempts to establish a connection, based on the retryIntervalForClientReroute value.

During automatic client reroute processing, the memberConnectTimeout property takes precedence over the loginTimeout property.

logWriter
The character output stream to which all logging and trace messages for the DataSource object are printed. The data type of this property is java.io.PrinterWriter. The default value is null, which means that no logging or tracing for the DataSource is output.

maxRetriesForClientReroute
During automatic client reroute, limits the number of retries if the primary connection to the data server fails.

The data type of this property is int.

The meaning of a retry and the default depend on the data server and the driver version:

- For connections to Db2 for z/OS data servers:
  - **Meaning of a retry:**
    - For version 3.66 or 4.16, or later, one retry means one attempt to connect to all members of the data sharing group other than the failed member, and to the group IP address.
    - For versions of the IBM Data Server Driver for JDBC and SQLJ before 3.66 or 4.16, one retry means an attempt to connect to one member of the data sharing group.
  - **Default:**
    - **Default starting with driver version 4.33:** When neither maxRetriesForClientReroute nor retryIntervalForClientReroute is set, and the initial connection to the data sharing group

is not established, the default maxRetriesForClientReroute value is 1, and the default retryIntervalForClientReroute value is 0.

- **Default before driver version 4.33:**
  - For version 3.66 or 4.16, or later, of the IBM Data Server Driver for JDBC and SQLJ, the default is 1.
  - For versions 3.64, 4.14, 3.65, or 4.15, the default is 5.
  - For versions of the IBM Data Server Driver for JDBC and SQLJ before 3.64 and 4.14, the connection is retried for 10 minutes. A wait time exists between retries that increases as the length of time from the first retry increases.

- **For connections to data servers other than Db2 for z/OS**:
  - **Meaning of a retry:** If enableClientAffinitiesList is set to `DB2BaseDataSource.NO` (2), an attempt to connect to the primary server and alternate servers counts as one retry.

    If enableClientAffinitiesList is set to `DB2BaseDataSource.YES` (1), an attempt to connect to each server that is specified by the clientRerouteAlternateServerName and clientRerouteAlternatePortNumber values counts as one retry. Each server connection is retried the number of times that is specified by maxRetriesForClientReroute.

    For connections to a Db2 pureScale instance:

    - For version 3.67 or 4.17 or later of the IBM Data Server Driver for JDBC and SQLJ, a retry is an attempt to connect to all members of the data server instance.
    - For versions of the IBM Data Server Driver for JDBC and SQLJ before 3.67 or 4.17, a retry is an attempt to connect to a single member.
  - **Default:**
    - **Default starting with driver version 4.33:** When neither maxRetriesForClientReroute nor retryIntervalForClientReroute is set, the connection is retried for 10 minutes.
    - **Default before driver version 4.33:** If enableClientAffinitiesList is set to `DB2BaseDataSource.NO` (2), and maxRetriesForClientReroute and retryIntervalForClientReroute are not set, the connection is retried for 10 minutes. A wait time exists between retries that increases as the length of time from the first retry increases.

      If enableClientAffinitiesList is DB2BaseDataSource.YES (1), the default is 3.

If the value of maxRetriesForClientReroute is 0, client reroute processing does not occur.

maxStatements

Controls an internal statement cache that is associated with a `Connection`. The data type of this property is int. Possible values are:

positive integer
Enables the internal statement cache for a `Connection`, and specifies the number of statements that the IBM Data Server Driver for JDBC and SQLJ keeps open in the cache.

0 or negative integer
Disables internal statement caching for the `Connection`. 0 is the default.

com.ibm.db2.jcc.DB2SimpleDataSource.maxStatements controls the internal statement cache that is associated with a `Connection` only when the `Connection` object is created. com.ibm.db2.jcc.DB2SimpleDataSource.maxStatements has no effect on caching in an existing `Connection` object.

com.ibm.db2.jcc.DB2SimpleDataSource.maxStatements applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

maxTransportObjectWaitTime

Specifies the maximum amount of time in seconds that an application waits for a transport object if the maxTransportObjects value has been reached. Transport objects are used for the connection

concentrator and sysplex workload balancing. When an application waits for longer than the maxTransportObjectWaitTime value, the global transport object pool throws an SQLException.

The default value for maxTransportObjectWaitTime is 1. Any negative value means that applications wait forever.

This property does not have a `setXXX` or a `getXXX` method.

onDataTruncation
Specifies the action that the IBM Data Server Driver for JDBC and SQLJ takes when an input value is inserted into a column, and the value is too large for that column. onDataTruncation applies only to version 4.33 or later of the driver. Possible values are:

DB2BaseDataSource.ON_DATA_TRUNCATION_WARNING_VALUE (1)
The IBM Data Server Driver for JDBC and SQLJ issues a warning if data truncation occurs. This value is the default.

DB2BaseDataSource.ON_DATA_TRUNCATION_THROW_EXCEPTION_VALUE (2)
The IBM Data Server Driver for JDBC and SQLJ throws an exception if data truncation occurs.

DB2BaseDataSource.ON_DATA_TRUNCATION_NO_ACTION_VALUE (3)
The IBM Data Server Driver for JDBC and SQLJ takes no action, which is the same as the behavior for driver versions before 4.33.

password
The password to use for establishing connections. The data type of this property is String. When you use the `DataSource` interface to establish a connection, you can override this property value by invoking this form of the `DataSource.getConnection` method:

```
getConnection(user, password);
```

portNumber
The port number where the DRDA server is listening for requests. The data type of this property is int.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

progressiveStreaming
Specifies whether the JDBC driver uses progressive streaming when progressive streaming is supported on the data source.

Db2 for z/OS Version 9.1 and later supports progressive streaming for LOBs and XML objects. Db2 on Linux, UNIX, and Windows systems Version 9.5 and later, and IBM Informix Version 11.50 and later support progressive streaming for LOBs.

With progressive streaming, also known as dynamic data format, the data source dynamically determines the most efficient mode in which to return LOB or XML data. This step is based on the size of the LOBs or XML objects. The value of the streamBufferSize parameter determines whether the data is materialized when it is returned.

The data type of progressiveStreaming is int. Valid values are `DB2BaseDataSource.YES` (1) and `DB2BaseDataSource.NO` (2). If the progressiveStreaming property is not specified, the progressiveStreaming value is `DB2BaseDataSource.NOT_SET` (0).

If the connection is to a data source that supports progressive streaming, and the value of progressiveStreaming is `DB2BaseDataSource.YES` or `DB2BaseDataSource.NOT_SET`, the JDBC driver uses progressive streaming to return LOBs and XML data.

If the value of progressiveStreaming is `DB2BaseDataSource.NO`, or the data source does not support progressive streaming, the way in which the JDBC driver returns LOB or XML data depends on the value of the fullyMaterializeLobData property.

queryCloseImplicit
Specifies whether cursors are closed immediately after all rows are fetched. queryCloseImplicit applies only to connections to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to z/OS Version 8 or later, and IBM Data Server Driver for JDBC and SQLJ type 4 connectivity or IBM

Data Server Driver for JDBC and SQLJ type 2 connectivityDb2 on Linux, UNIX, and Windows systems Version 9.7 or later. Possible values are:

DB2BaseDataSource.QUERY_CLOSE_IMPLICIT_YES (1)
Close cursors immediately after all rows are fetched.

A value of `DB2BaseDataSource.QUERY_CLOSE_IMPLICIT_YES` can provide better performance because this setting results in less network traffic.

DB2BaseDataSource.QUERY_CLOSE_IMPLICIT_NO (2)
Do not close cursors immediately after all rows are fetched.

DB2BaseDataSource.QUERY_CLOSE_IMPLICIT_COMMIT (3)
Perform these actions:

- Implicitly close the cursor after all rows are fetched.
- If the application is in autocommit mode, implicitly send a commit request to the data source for the current unit of work.

Important: When this value is set, there might be impacts on other resources, just as an explicit commit operation might impact other resources. For example, other non-held cursors are closed, LOB locators go out of scope, progressive references are reset, and scrollable cursors lose their position.

Restriction: The following restrictions apply to QUERY_CLOSE_IMPLICIT_COMMIT behavior:

- This behavior applies only to SELECT statements that are issued by the application. It does not apply to SELECT statements that are generated by the IBM Data Server Driver for JDBC and SQLJ.
- If QUERY_CLOSE_IMPLICIT_COMMIT is set, and the application is not in autocommit mode, the driver uses the default behavior (QUERY_CLOSE_IMPLICIT_NOT_SET behavior). If QUERY_CLOSE_IMPLICIT_COMMIT is the default behavior, the driver uses QUERY_CLOSE_IMPLICIT_YES behavior.
- If QUERY_CLOSE_IMPLICIT_COMMIT is set, and the data source does not support QUERY_CLOSE_IMPLICIT_COMMIT behavior, the driver uses QUERY_CLOSE_IMPLICIT_YES behavior.
- This behavior is not supported for batched statements.
- This behavior is supported on an XA Connection only when the connection is in a local transaction.

DB2BaseDataSource.QUERY_CLOSE_IMPLICIT_NOT_SET (0)
This value is the default. The following table describes the behavior for a connection to each type of data source.

Data source	Version	Data sharing environment	Behavior
Db2 for z/OS	Version 10	Data sharing or non-data sharing	QUERY_CLOSE_IMPLICIT_COMMIT
Db2 for z/OS	Version 9 with APAR PK68746	Non-data sharing, or in a data sharing group but not in coexistence mode with Version 8 members	QUERY_CLOSE_IMPLICIT_COMMIT
Db2 for z/OS	Version 9 without APAR PK68746	Non-data sharing, or in a data sharing group but not in coexistence mode with Version 8 members	QUERY_CLOSE_IMPLICIT_YES
Db2 for z/OS	Version 9 with APAR PK68746	In a data sharing group in coexistence mode with Version 8 members	QUERY_CLOSE_IMPLICIT_COMMIT

Data source	Version	Data sharing environment	Behavior
Db2 for z/OS	Version 9 without APAR PK68746	In a data sharing group in coexistence mode with Version 8 members	QUERY_CLOSE_IMPLICIT_YES
Db2 for z/OS	Version 8 with or without APAR PK68746		QUERY_CLOSE_IMPLICIT_YES
Db2 on Linux, UNIX, and Windows systems	Version 9.7		QUERY_CLOSE_IMPLICIT_YES

queryDataSize

Specifies a hint that is used to control the amount of query data, in bytes, that is returned from the data source on each fetch operation. This value can be used to optimize the application by controlling the number of trips to the data source that are required to retrieve data.

Use of a larger value for queryDataSize can result in less network traffic, which can result in better performance. For example, if the result set size is 50 KB, and the value of queryDataSize is 32767 (32 KB), two trips to the database server are required to retrieve the result set. However, if queryDataSize is set to 65535 (64 KB), only one trip to the data source is required to retrieve the result set.

The following table lists minimum, maximum, and default values of queryDataSize for each data server, for the IBM Data Server Driver for JDBC and SQLJ, version 4.31 (Db2 11.5.7) or later.

Table 37. Default, minimum, and maximum values of queryDataSize for IBM Data Server Driver for JDBC and SQLJ, version 4.31 (Db2 11.5.7) or later

Data source	Product Version	Default	Minimum	Maximum	Valid values"1" on page 241
Db2 on Linux, UNIX, and Windows systems	All supported versions	32767	4096	10485760	Valid values between 4096 and 262143: 4096 - 32767, 98303, 131071, 163839, 196607, 229375, 262143. Valid values greater than 262143: Any integer multiple of 32768 that is less than or equal to 10485760.
IBM Informix	All supported versions	32767	4096	10485760	4096 - 10485760
Db2 for IBM i	All supported versions	32767	4096	10485760	Valid values between 4096 and 262143: 4096 - 65535, 98303, 131071, 163839, 196607, 229375, 262143. Valid values greater than 262143: Any integer multiple of 32768 that is less than or equal to 10485760.
Db2 for z/OS	All supported versions (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity)	32767	32767	10452991	Valid values between 4096 and 262143: 4096 - 32767, 98303, 131071, 163839, 196607, 229375, 262143. Valid values greater than 262143: 10452991, or any integer multiple of 32768 that is less than 10452991.

Table 37. Default, minimum, and maximum values of queryDataSize for IBM Data Server Driver for JDBC and SQLJ, version 4.31 (Db2 11.5.7) or later (continued)

Data source	Product Version	Default	Minimum	Maximum	Valid values[“1” on page 241]
Db2 for z/OS	All supported versions (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity)	32767	32767	1048575	32767, 65535, 98303, 131071, 163839, 196607, 229375, 262143, 294911, 327679, 360447, 393215, 425983, 458751, 491519, 524287, 557055, 589823, 622591, 655359, 688127, 720895, 753663, 786431, 819199, 851967, 884735, 917503, 950271, 983039, 1015807, 1048575

Note:

1. If you specify a value between the minimum and maximum value that is not a valid value, the IBM Data Server Driver for JDBC and SQLJ sets queryDataSize to the nearest valid value.

The following table lists minimum, maximum, and default values of queryDataSize for each data server, for the IBM Data Server Driver for JDBC and SQLJ, version 4.29 (Db2 11.5.6) or earlier.

Table 38. Default, minimum, and maximum values of queryDataSize for IBM Data Server Driver for JDBC and SQLJ, version 4.29 (Db2 11.5.6) or earlier

Data source	Product Version	Default	Minimum	Maximum	Valid values[“1” on page 241]
Db2 on Linux, UNIX, and Windows systems	All supported versions	32767	4096	262143	4096 - 32767, 98303, 131071, 163839, 196607, 229375, 262143
IBM Informix	All supported versions	32767	4096	10485760	4096 - 10485760
Db2 for IBM i	All supported versions	32767	4096	262143	4096 - 65535, 98303, 131071, 163839, 196607, 229375, 262143
Db2 for z/OS	All supported versions (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity)	32767	32767	262143	32767, 65535, 98303, 131071, 163839, 196607, 229375, 262143
Db2 for z/OS	All supported versions (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity)	32767	32767	1048575	32767, 65535, 98303, 131071, 163839, 196607, 229375, 262143, 294911, 327679, 360447, 393215, 425983, 458751, 491519, 524287, 557055, 589823, 622591, 655359, 688127, 720895, 753663, 786431, 819199, 851967, 884735, 917503, 950271, 983039, 1015807, 1048575

Note:

1. If you specify a value between the minimum and maximum value that is not a valid value, the IBM Data Server Driver for JDBC and SQLJ sets queryDataSize to the nearest valid value.

queryTimeoutInterruptProcessingMode

Specifies what happens when the query timeout interval for a `Statement` object expires. Valid values are:

DB2BaseDataSource.- INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL (1)

Specifies that when the query timeout interval for a `Statement` object expires, the IBM Data Server Driver for JDBC and SQLJ cancels the currently executing SQL statement. The IBM Data Server Driver for JDBC and SQLJ also throws an exception with SQL error -952, if the data server supports the interruption of SQL statements. If the data server does not support the interruption of SQL statements, the driver throws an exception that indicates that the feature is not supported.

For connections to data servers other than Db2 for z/OS, INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL is the default.

For connections to Db2 for z/OS data servers, INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL is not a possible value. If it is specified, the driver uses INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET instead.

DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET (2)

When the queryTimeout interval for a `Statement` object expires, one of the following actions occurs:

- For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, the underlying socket is dropped and the connection is closed.
- For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, the data server issues a CANCEL THREAD LOCAL command and terminates the underlying RRSAF thread. As a result, the connection is closed.
- For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 on Linux, UNIX, and Windows systems, DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET is not supported. An exception with SQL error -4450 is thrown.

For connections to data servers other than Db2 for z/OS, when the `Statement` object times out:

- If automatic client reroute is not enabled and enableSysplexWLB is set to `false`, an exception with SQL error code -4499 is thrown. Any subsequent operations on the `Statement` object, or on any other `Statement` objects that were created from the same connection receive an `Exception` that indicates that the connection is closed. After a `Statement` object times out, the application must establish a new connection before it can execute a new transaction.
- If automatic client reroute is enabled, and enableSysplexWLB is set to `false`, the IBM Data Server Driver for JDBC and SQLJ tries to reestablish a connection. If a new connection is successfully reestablished, the driver returns an SQL error code of -4498. However, the driver does not execute the timed-out SQL statements again, even if enableSeamlessFailover is set to `DB2BaseDataSource.YES` (1).
- If enableSysplexWLB is set to `true`, the IBM Data Server Driver for JDBC and SQLJ tries to reestablish a connection. If a new connection is successfully reestablished, the driver returns an SQL error code of -30108. However, the driver does not execute the timed-out SQL statements again, even if enableSeamlessFailover is set to `DB2BaseDataSource.YES` (1).

For connections to Db2 for z/OS, when the `Statement` object times out:

- If enableSysplexWLB is set to `false`, an exception with SQL error code -4499 is thrown. Any subsequent operations on the `Statement` object, or on any other `Statement` objects that were created from the same connection receive an `Exception` that indicates that the connection is closed. After a `Statement` object times out, the application must establish a new connection before it can execute a new transaction.
- If enableSysplexWLB is set to `true`, the IBM Data Server Driver for JDBC and SQLJ tries to reestablish a connection. If a new connection is successfully reestablished, the driver returns an SQL error code of -30108. However, the driver does not execute the timed-out SQL statements again, even if enableSeamlessFailover is set to `DB2BaseDataSource.YES` (1).

resultSetHoldability
Specifies whether cursors remain open after a commit operation. The data type of this property is int. Valid values are:

DB2BaseDataSource.HOLD_CURSORS_OVER_COMMIT (1)
Leave cursors open after a commit operation.

This setting is not valid for a connection that is part of a distributed (XA) transaction.

DB2BaseDataSource.CLOSE_CURSORS_AT_COMMIT (2)
Close cursors after a commit operation.

DB2BaseDataSource.NOT_SET (0)
This value is the default. The behavior is:

- For connections that are part of distributed (XA) transactions, cursors are closed after a commit operation.
- For connections that are not part of a distributed transaction:
  - For connections to all versions of Db2 for z/OS, Db2 on Linux, UNIX, and Windows systems, or Db2 for IBM i servers, or to Cloudscape Version 8.1 or later servers, cursors remain open after a commit operation.
  - For connections to all versions of IBM Informix, or to Cloudscape versions earlier than Version 8.1, cursors are closed after a commit operation.

retrieveMessagesFromServerOnGetMessage
Specifies whether JDBC `SQLException.getMessage` or `SQLWarning.getMessage` calls cause the IBM Data Server Driver for JDBC and SQLJ to invoke a Db2 for z/OS stored procedure that retrieves the message text for the error. The data type of this property is boolean. The default is `false`, which means that the full message text is not returned to the client.

For example, if retrieveMessagesFromServerOnGetMessage is set to `true`, a message similar to this one is returned by `SQLException.getMessage` after an attempt to perform an SQL operation on nonexistent table ADMF001.NO_TABLE:

```
ADMF001.NO_TABLE IS AN UNDEFINED NAME. SQLCODE=-204,
SQLSTATE=42704, DRIVER=3.50.54
```

If retrieveMessagesFromServerOnGetMessage is set to `false`, a message similar to this one is returned:

```
DB2 SQL Error: SQLCODE=-204, SQLSTATE=42704, DRIVER=3.50.54
```

An alternative to setting this property to `true` is to use only the `DB2Sqlca.getMessage` method for IBM Data Server Driver for JDBC and SQLJ in applications. Both techniques result in a stored procedure call, which starts a unit of work.

retryIntervalForClientReroute
For automatic client reroute, specifies the amount of time in seconds between connection retries.

The data type of this property is int.

The meaning of a retry and the default depend on the data server and the driver version:

- For connections to Db2 for z/OS data servers:
  - **Meaning of a retry:**
    - For version 3.66 or 4.16, or later, one retry means one attempt to connect to all members of the data sharing group other than the failed member, and to the group IP address.
    - For versions of the IBM Data Server Driver for JDBC and SQLJ before 3.66 or 4.16, one retry means an attempt to connect to one member of the data sharing group.
  - **Default:**

- **Default starting with driver version 4.33:** When neither maxRetriesForClientReroute nor retryIntervalForClientReroute is set, and the initial connection to the data sharing group is not established, the default maxRetriesForClientReroute value is 1, and the default retryIntervalForClientReroute value is 0.
- **Default before driver version 4.33:**
  - For version 3.66 or 4.16, or later, of the IBM Data Server Driver for JDBC and SQLJ, the default is 0.
  - For versions of the IBM Data Server Driver for JDBC and SQLJ before 3.64 and 4.14, the connection is retried for 10 minutes. A wait time exists between retries that increases as the length of time from the first retry increases.

- **For connections to data servers other than Db2 for z/OS**:
  - **Meaning of a retry:** If enableClientAffinitiesList is set to `DB2BaseDataSource.NO` (2), an attempt to connect to the primary server and alternate servers counts as one retry.

    If enableClientAffinitiesList is set to `DB2BaseDataSource.YES` (1), an attempt to connect to each server that is specified by the clientRerouteAlternateServerName and clientRerouteAlternatePortNumber values counts as one retry. Each server connection is retried the number of times that is specified by maxRetriesForClientReroute.

    For connections to a Db2 pureScale instance:

    - For version 3.67 or 4.17 or later of the IBM Data Server Driver for JDBC and SQLJ, a retry is an attempt to connect to all members of the data server instance.
    - For versions of the IBM Data Server Driver for JDBC and SQLJ before 3.67 or 4.17, a retry is an attempt to connect to a single member.
  - **Default:**
    - **Default starting with driver version 4.33:** When neither maxRetriesForClientReroute nor retryIntervalForClientReroute is set, the connection is retried for 10 minutes.
    - **Default before driver version 4.33:** If enableClientAffinitiesList is set to `DB2BaseDataSource.NO` (2), and maxRetriesForClientReroute and retryIntervalForClientReroute are not set, the connection is retried for 10 minutes. A wait time exists between retries that increases as the length of time from the first retry increases.

      If enableClientAffinitiesList is DB2BaseDataSource.YES (1), the default is 3.

securityMechanism
Specifies the DRDA security mechanism. The data type of this property is int. Possible values are:

CLEAR_TEXT_PASSWORD_SECURITY (3)
User ID and password

USER_ONLY_SECURITY (4)
User ID only

ENCRYPTED_PASSWORD_SECURITY (7)
User ID, encrypted password

ENCRYPTED_USER_AND_PASSWORD_SECURITY (9)
Encrypted user ID and password

KERBEROS_SECURITY (11)
Kerberos. This value does not apply to connections to IBM Informix.

ENCRYPTED_USER_AND_DATA_SECURITY (12)
Encrypted user ID and encrypted security-sensitive data. This value applies to connections to Db2 for z/OS only.

ENCRYPTED_USER_PASSWORD_AND_DATA_SECURITY (13)
Encrypted user ID and password, and encrypted security-sensitive data. This value does not apply to connections to IBM Informix.

PLUGIN_SECURITY (15)
Plug-in security. This value applies to connections to Db2 on Linux, UNIX, and Windows systems only.

ENCRYPTED_USER_ONLY_SECURITY (16)
Encrypted user ID. This value does not apply to connections to IBM Informix.

TLS_CLIENT_CERTIFICATE_SECURITY (18)
Client certificate security, by using SSL. This value applies to connections to Db2 for z/OS Version 10 and later only.

TOKEN_SECURITY (19)
Token authentication. This value applies to connections to Db2 on Linux, UNIX, and Windows systems, Version 11.5 Mod Pack 4 or later, and the IBM Data Server Driver for JDBC and SQLJ, version 4.27.22 or later.

If securityMechanism is specified, the specified security mechanism is the only mechanism that is used. If the security mechanism is not supported by the connection, an exception is thrown.

Important:

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ:

- The default security mechanism is ENCRYPTED_USER_AND_PASSWORD_SECURITY. If the data server does not support ENCRYPTED_USER_AND_PASSWORD_SECURITY, but supports CLEAR_TEXT_PASSWORD_SECURITY, the driver changes the security mechanism to CLEAR_TEXT_PASSWORD_SECURITY and attempts to connect to the data server. The connection retry using CLEAR_TEXT_PASSWORD_SECURITY might cause a slight performance impact. Any other mismatch in security mechanism support between the requester and the data server results in an error.
- A connection to a Db2 for z/OS subsystem or data sharing group that uses the default security mechanism of ENCRYPTED_USER_AND_PASSWORD_SECURITY and AES encryption is successful only if the z/OS Integrated Cryptographic Service Facility (ICSF) is enabled on the z/OS system where each subsystem or data sharing member is installed. ICSF is required for decrypting the user ID and password. If ICSF is not installed, you need to set the security mechanism to CLEAR_TEXT_PASSWORD_SECURITY.

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default security mechanism is CLEAR_TEXT_PASSWORD_SECURITY. If the data server does not support CLEAR_TEXT_PASSWORD_SECURITY, but supports ENCRYPTED_USER_AND_PASSWORD_SECURITY, the driver changes the security mechanism to ENCRYPTED_USER_AND_PASSWORD_SECURITY and attempts to connect to the data server. Any other mismatch in security mechanism support between the requester and the data server results in an error.

This property does not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Security mechanisms ENCRYPTED_PASSWORD_SECURITY, ENCRYPTED_USER_AND_PASSWORD_SECURITY, ENCRYPTED_USER_AND_DATA_SECURITY, ENCRYPTED_USER_PASSWORD_AND_DATA_SECURITY, and ENCRYPTED_USER_ONLY_SECURITY use DRDA encryption. DRDA encryption is not intended to provide confidentiality and integrity of passwords or data over a network that is not secure, such as the Internet. DRDA encryption uses an anonymous key exchange, Diffie-Hellman, which does not provide authentication of the server or the client. DRDA encryption is vulnerable to man-in-the-middle attacks.

sendDataAsIs
Specifies that the IBM Data Server Driver for JDBC and SQLJ does not convert input parameter values to the target column data types. The data type of this property is boolean. The default is `false`.

You must use this property only for applications that always ensure that the data types in the application match the data types in the corresponding database tables.

serverBidiStringType

Used if enableBidiLayoutTransformation is enabled. Specifies the string type that is used by the server. The data type of this property is int. serverBidiStringType takes on the same possible values as clientBidiStringType.

serverName

The host name or the TCP/IP address of the data source. The data type of this property is String.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

sqljAvoidTimeStampConversion

Specifies whether the IBM Data Server Driver for JDBC and SQLJ prevents Java's adjustment of a timestamp value, and returns an unadjusted value during data retrieval, in either of the following cases:

- When the date portion of the value is in the range of October 5, 1582 to October 14, 1582, inclusive.
- When the system on which the data server resides adjusts for daylight saving time. Adjusting for daylight saving time means:
  - Moving the clock forward by one hour on a specified date in the spring. The length of that day is 23 hours.
  - Moving the clock backward by one hour on a specified date in the fall. The length of that day is 25 hours.

Possible values for `sqljAvoidTimeStampConversion` are:

true

During data retrieval, the a timestamp value is not adjusted.

When you set the sqljAvoidTimeStampConversion property to `true`, you need to use the `ResultSet.getString` method to retrieve timestamp values in `String` format. If you use `ResultSet` methods that specify a Java `Calendar` parameter and return a `Timestamp` object, Java application programming interfaces modify the data, and the driver cannot control timestamp conversion.

false

During data retrieval, a timestamp value is adjusted. `false` is the default.

This property applies to SQLJ and JDBC applications.

sslCertLocation

Specifies that an application can configure the location of a trusted certificate file. For applications that have the database server certificate, sslCertLocation is the only property that is needed to be configured to instruct IBM Data Server Driver for JDBC and SQLJ to trust the certificate for SSL connections. This property removes the need to import the certificate into a Java truststore database and related driver configurations.

The default value for sslCertLocation is provided by the db2.jcc.sslCertLocation configuration property. If the db2.jcc.sslCertLocation configuration property is not specified, sslTruststoreLocation, and sslCertLocation properties are not configured, and sslConnection is set to `true`, IBM Data Server Driver for JDBC and SQLJ uses the default truststore for the Java runtime environment.

The sslCertLocation property accepts certificate location values in the following forms:

- File extensions: .arm, .pem, .cert, .crt, and .der.
- Full path to the certificate file: `sslCertLocation=/path/to/cert.arm`
- Path relative to the current class path:`sslCertLocation=classpath:relative/cert.arm`
- DER-encoded certificates in binary or Base64 ASCII encoding. If the certificate is provided in Base64 encoding, the file content must be bound at the beginning by `-----BEGIN CERTIFICATE-----` and at the end by `-----END CERTIFICATE-----`.

sslCipherSuites

Specifies the set of cipher suites to use when you establish SSL connections to the server. Configure this property only when you would not like to use the default cipher suites from the JRE (Java Runtime Environment). Specify the names of cipher suites as string values separated by commas.

sslClientHostnameValidation

Specifies whether the IBM Data Server Driver for JDBC and SQLJ performs client host name validation when establishing a connection to a data server that uses transport layer security (TLS). Host name validation is performed according to the standard that is specified in IETF RFC 6125.

sslClientHostnameValidation can have one of the following values:

BASIC
Specifies that host name validation is enabled. During the TLS handshake, when the data server sends its certificate to the driver, the driver checks whether the host name or its corresponding IP address in the certificate matches the host name or corresponding IP address that the application provides to the driver.

OFF
Specifies that host name validation is disabled. This is the default.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS and to Db2 on Linux, UNIX, and Windows systems .

sslConnection

Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses an SSL socket to connect to the data source. If sslConnection is set to `true`, the connection uses an SSL socket. If sslConnection is set to `false`, the connection uses a plain socket.

The default value for sslConnection is provided by the db2.jcc.sslConnection configuration property. If the db2.jcc.sslConnection configuration property is also not specified, the default value for sslConnection is `false`.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

sslTrustStoreLocation

Specifies the full path name of the Java truststore on the client that contains the server certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the sslConnection property is set to `true`.

If sslTrustStoreLocation is set, and sslConnection is set to `true`, the IBM Data Server Driver for JDBC and SQLJ uses the sslTrustStoreLocation value instead of the value in the javax.net.ssl.trustStore Java property.

The default value for sslTrustStoreLocation is provided by the db2.jcc.sslTrustStoreLocation configuration property. If the db2.jcc.sslTrustStoreLocation configuration property is also not specified, the default value for sslTrustStoreLocation is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

sslTrustStorePassword

Specifies the password for the Java truststore on the client that contains the server certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the sslConnection property is set to `true`.

If sslTrustStorePassword is set, and sslConnection is set to `true`, the IBM Data Server Driver for JDBC and SQLJ uses the sslTrustStorePassword value instead of the value in the javax.net.ssl.trustStorePassword Java property.

The default value for sslTrustStorePassword is provided by the db2.jcc.sslTrustStorePassword configuration property. If the db2.jcc.sslTrustStorePassword configuration property is also not specified, the default value for sslTrustStorePassword is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

sslTrustStoreType
Specifies the type of a trusted certificate file. The `sslTrustStoreType` property is for Db2 for z/OS, Db2 on Linux, UNIX, and Windows systems, and IBM Informix of a T4 SSL connection.

The default value of `sslTrustStoreType` is `NULL` (NOT SET). If `sslTrustStoreType` is `NULL`, then the JRE's default trust store type is applied to load the trust Store file for the SSL connection.

sslVersion
Specifies the SSL version or TLS protocol level that an application can use for an SSL connection. The default value of sslVersion is `null` (not set). If sslVersion is not defined on the Connection or DataSource object, the default TLS level or SSL version for the Java Runtime Environment is applied for the SSL connection. Examples of sslVersion values are TLSv1.3 and SSLv3.

stripTrailingZerosForDecimalNumbers
Specifies whether the IBM Data Server Driver for JDBC and SQLJ removes trailing zeroes when it retrieves data from a DECFLOAT, DECIMAL, or NUMERIC column. This property is meaningful only if the SDK for Java is Version 1.5 or later. The data type of this property is int.

Possible values are:

DB2BaseDataSource.NOT_SET (0)
The IBM Data Server Driver for JDBC and SQLJ does not remove trailing zeroes from the retrieved value. This value is the default.

DB2BaseDataSource.YES (1)
The IBM Data Server Driver for JDBC and SQLJ removes trailing zeroes when it retrieves a value from a DECFLOAT, DECIMAL, or NUMERIC column as a `java.math.BigDecimal` object.

For example, when the driver retrieves the value 234.04000, it returns the value 234.04 to the application.

DB2BaseDataSource.NO (2)
The IBM Data Server Driver for JDBC and SQLJ does not remove trailing zeroes from the retrieved value.

timerLevelForQueryTimeOut
Specifies the level at which the IBM Data Server Driver for JDBC and SQLJ creates a `java.util.Timer` object for waiting for query execution to time out. Possible values are:

DB2BaseDataSource.QUERYTIMEOUT_STATEMENT_LEVEL (1)
The IBM Data Server Driver for JDBC and SQLJ creates a `Timer` object for each `Statement` object. When the `Statement` object is closed, the driver deletes the `Timer` object. This value is the default before IBM Data Server Driver for JDBC and SQLJ version 4.26.

DB2BaseDataSource.QUERYTIMEOUT_CONNECTION_LEVEL (2)
The IBM Data Server Driver for JDBC and SQLJ creates a `Timer` object for each `Connection` object. When the `Connection` object is closed, the driver deletes the `Timer` object. This value is the default for IBM Data Server Driver for JDBC and SQLJ version 4.26 or later.

When timerLevelForQueryTimeOut is set to QUERYTIMEOUT_CONNECTION_LEVEL in a connection pooling environment, the number of `Timer` objects in the process is equal to the number of `Connection` objects in the pool. The timer thread is active for the lifetime of all `Connection` objects in the pool.

DB2BaseDataSource.QUERYTIMEOUT_DISABLED (-1)
The IBM Data Server Driver for JDBC and SQLJ does not create a `Timer` object to control query execution timeout.

timestampFormat
Specifies the format in which the result of the `ResultSet.getString` or `CallableStatement.getString` method against a TIMESTAMP column is returned. The data type of timestampFormat is int.

Possible values of timestampFormat are:

Constant	Integer value	Format
com.ibm.db2.jcc.DB2BaseDataSource.ISO	1	*yyyy-mm-dd-hh.mm.ss.nnnnnnnnn*"1" on page 249
com.ibm.db2.jcc.DB2BaseDataSource.JDBC	5	*yyyy-mm-dd hh:mm:ss.nnnnnnnnn*"1" on page 249

Note:

1. The number of digits in the fractional part of the timestamp depends on the precision of the TIMESTAMP(*p*) column in the source table. If *p*<9, *p* digits are returned. If *p*>=9, 9 digits are returned, and the remaining digits are truncated.

The default is com.ibm.db2.jcc.DB2BaseDataSource.JDBC.

timestampFormat affects the format of output only.

timestampPrecisionReporting
Specifies whether trailing zeroes are truncated in the result of a Resultset.getString call for a TIMESTAMP value. The data type of this property is int. Possible values are:

TIMESTAMP_JDBC_STANDARD (1)
Trailing zeroes are truncated in the result of a Resultset.getString call for a TIMESTAMP value. This value is the default.

For example:

- A TIMESTAMP value of 2009-07-19-10.12.00.000000 is truncated to 2009-07-19-10.12.00.0 after retrieval.
- A TIMESTAMP value of 2009-12-01-11.30.00.100000 is truncated to 2009-12-01-11.30.00.1 after retrieval.

TIMESTAMP_ZERO_PADDING (2)
Trailing zeroes are not truncated in the result of a Resultset.getString call for a TIMESTAMP value.

traceDirectory
Specifies a directory into which trace information is written. The data type of this property is String. When traceDirectory is specified, trace information for multiple connections on the same DataSource is written to multiple files.

When traceDirectory is specified, a connection is traced to a file named traceFile_*origin*_*n*.

n is the *n*th connection for a DataSource.

origin indicates the origin of the log writer that is in use. Possible values of *origin* are:

cpds
The log writer for a DB2ConnectionPoolDataSource object.

driver
The log writer for a DB2Driver object.

global
The log writer for a DB2TraceManager object.

sds
The log writer for a DB2SimpleDataSource object.

xads
The log writer for a DB2XADataSource object.

If the traceFile property is also specified, the traceDirectory value is not used.

traceFile
Specifies the name of a file into which the IBM Data Server Driver for JDBC and SQLJ writes trace information. The data type of this property is `String`. The traceFile property is an alternative to the logWriter property for directing the output trace stream to a file.

The traceFile value cannot have any of the following file extensions: `exe`, `dll`, `bat`, `jar`, `vbs`, `py`, `js`, `jsp`, `jspx`, `msi`, `com`, `inf`, `ipa`, `osx`, `pif`, `run`, `wsh`, `zip`, or `asp`.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, the db2.jcc.override.traceFile configuration property value overrides the `traceFile` property value.

Recommendation: Set the db2.jcc.override.traceFile configuration property, rather than setting the traceFile property for individual connections.

traceFileAppend
Specifies whether to append to or overwrite the file that is specified by the traceFile property. The data type of this property is boolean. The default is `false`, which means that the file that is specified by the traceFile property is overwritten.

traceLevel
Specifies what to trace. The data type of this property is int.

You can specify one or more of the following traces with the traceLevel property:

- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_NONE` (X'00')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTION_CALLS` (X'01')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_STATEMENT_CALLS` (X'02')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_CALLS` (X'04')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRIVER_CONFIGURATION` (X'10')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTS` (X'20')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS` (X'40')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_META_DATA` (X'80')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_PARAMETER_META_DATA` (X'100')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DIAGNOSTICS` (X'200')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SQLJ` (X'400®')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_META_CALLS` (X'2000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DATASOURCE_CALLS` (X'4000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_LARGE_OBJECT_CALLS` (X'8000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_T2ZOS` (X'10000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSTEM_MONITOR` (X'20000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_TRACEPOINTS` (X'40000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSPLEX` (X'80000') (for version 3.68 or 4.18, or later, of the IBM Data Server Driver for JDBC and SQLJ, and connections to Db2 for z/OS data sharing groups)
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL` (X'FFFFFFFF')

To specify more than one trace, use one of these techniques:

- Use bitwise OR (|) operators with two or more trace values. For example, to trace DRDA flows and connection calls, specify this value for traceLevel:

```
TRACE_DRDA_FLOWS|TRACE_CONNECTION_CALLS
```

- Use a bitwise complement (~) operator with a trace value to specify all except a certain trace. For example, to trace everything except DRDA flows, specify this value for traceLevel:

```
 ~TRACE_DRDA_FLOWS
```

traceFileCount
Specifies the maximum number of trace files for circular tracing. The IBM Data Server Driver for JDBC and SQLJ uses this property only when traceOption is set to `DB2BaseDataSource.TRACE_OPTION_CIRCULAR` (1). The data type of this property is int. The default value is 2.

traceFileSize
Specifies the maximum size of each trace file, for circular tracing. The IBM Data Server Driver for JDBC and SQLJ uses this property only when traceOption is set to `DB2BaseDataSource.TRACE_OPTION_CIRCULAR` (1). The data type of this property is int. The default value is 10485760 (10 MB).

traceOption
Specifies how trace data is collected. The data type of this property is int. Possible values are:

`DB2BaseDataSource.NOT_SET` (0)
Specifies that a single trace file is generated, and that there is no limit to the size of the file. This value is the default.

If the value of traceOption is NOT_SET, the traceFileSize and traceFileCount properties are ignored.

`DB2BaseDataSource.TRACE_OPTION_CIRCULAR` (1)
Specifies that the IBM Data Server Driver for JDBC and SQLJ does circular tracing. Circular tracing is done as follows:

1. When an application writes its first trace record, the driver creates a file.
2. The driver writes trace data to the file.
3. When the size of the file is equal to the value of property traceFileSize, the driver creates another file.
4. The driver repeats steps "2" on page 251 and "3" on page 251 until the number of files to where data is written is equal to the value of property traceFileCount.
5. The driver writes data to the first trace file, overwriting the existing data.
6. The driver repeats steps "3" on page 251 through "5" on page 251 until the application completes.

The file names for the trace files are the file names that are determined by the traceFile or traceDirectory property. The file name is appended with .1 for the first file, .2 for the second file, and so on.

useJDBC41DefinitionForGetColumns
Specifies whether the `DatabaseMetaData.getColumns` method returns a result set with a column with the name SCOPE_CATALOG or SCOPE_CATLOG. Possible values are:

`DB2BaseDataSource.NOT_SET` (0)
Specifies that for version 4.13 or later of the IBM Data Server Driver for JDBC and SQLJ, the result set from `DatabaseMetaData.getColumns` contains a column named SCOPE_CATALOG. For version 4.12 or earlier of the IBM Data Server Driver for JDBC and SQLJ, that column is named SCOPE_CATLOG.

`DB2BaseDataSource.YES` (1)
Specifies that for version 4.13 or later of the IBM Data Server Driver for JDBC and SQLJ, the result set from `DatabaseMetaData.getColumns` contains a column named SCOPE_CATALOG. For version 4.12 or earlier of the IBM Data Server Driver for JDBC and SQLJ, that column is named SCOPE_CATLOG.

`DB2BaseDataSource.NO` (2)
Specifies that for all versions of the IBM Data Server Driver for JDBC and SQLJ, the result set from `DatabaseMetaData.getColumns` contains a column named SCOPE_CATLOG.

useJDBC4DataType
Specifies the data types that the IBM Data Server Driver for JDBC and SQLJ, version 4.27 or later, returns to an application for column data of the GRAPHIC, VARGRAPHIC, or DBCLOB data types. Possible values are:

DB2BaseDataSource.NOT_SET (0)
This value is the default. The behavior is the same as for DB2BaseDataSource.YES.

DB2BaseDataSource.YES (1)
Specifies that when data is retrieved from columns with the GRAPHIC, VARGRAPHIC, or DBCLOB data types, the IBM Data Server Driver for JDBC and SQLJ returns data of the following data types:

Column data type	Data type of returned data
GRAPHIC	NCHAR
VARGRAPHIC	NVARCHAR
DBCLOB	NCLOB

These returned data types comply with the JDBC 4.0 specification.

DB2BaseDataSource.NO (2)
Specifies that when data is retrieved from columns with the GRAPHIC, VARGRAPHIC, or DBCLOB data types, the IBM Data Server Driver for JDBC and SQLJ returns data with the following data types:

Column data type	Data type of returned data
GRAPHIC	CHAR
VARGRAPHIC	VARCHAR
DBCLOB	CLOB

These data types are the same data types that are returned for IBM Data Server Driver for JDBC and SQLJ version 4.26 or earlier.

user
The user ID to use for establishing connections. The data type of this property is String. When you use the DataSource interface to establish a connection, you can override this property value by invoking this form of the DataSource.getConnection method:

```
getConnection(user, password);
```

xaNetworkOptimization
Specifies whether XA network optimization is enabled for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. You might need to disable the XA network optimization in an environment in which an XA Start and XA End are issued from one Java process, and an XA Prepare and an XA Commit are issued from another Java process. With XA network optimization, the XA Prepare can reach the data source before the XA End, which results in an XAER_PROTO error. To prevent the XAER_PROTO error, disable the XA network optimization.

The default is true, which means that XA network optimization is enabled. If xaNetworkOptimization is false, which means that XA network optimization is disabled, the driver closes any open cursors at XA End time.

xaNetworkOptimization can be set on a DataSource object, or in the *url* parameter in a getConnection call. The value of xaNetworkOptimization cannot be changed after a connection is obtained.

Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 servers

Some of the IBM Data Server Driver for JDBC and SQLJ properties apply to Db2 data servers only.

Unless otherwise noted, all properties are in `com.ibm.db2.jcc.DB2BaseDataSource`.

Those properties are:

clientAccountingInformation
Specifies accounting information for the current client for the connection. This information is for client accounting purposes. This value can change during a connection. The data type of this property is . The maximum length is 255 bytes. A Java empty string ("") is valid for this value, but the Java `null` value is not valid.

clientApplicationInformation
Specifies the application or transaction name of the end user's application. You can use this property to provide the identity of the client end user for accounting and monitoring purposes. This value can change during a connection. The data type of this property is . For a Db2 for z/OS server, the maximum length is 32 bytes. For a Db2 on Linux, UNIX, and Windows systems server, the maximum length is 255 bytes. A Java empty string ("") is valid for this value, but the Java `null` value is not valid.

clientProgramId
Specifies a value for the client program ID that can be used to identify the end user. The data type of this property is , and the length is 80 bytes. If the program ID value is less than 80 bytes, the value must be padded with blanks.

clientProgramName
Specifies an application ID that is fixed for the duration of a physical connection for a client. The value of this property becomes the correlation ID on a Db2 for z/OS server. Database administrators can use this property to correlate work on a Db2 for z/OS server to client applications. The data type of this property is . The maximum length is 128 bytes. If this value is `null`, the IBM Data Server Driver for JDBC and SQLJ supplies a value of db2jcc*thread-name*.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

clientUser
Specifies the name of the user on whose behalf the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_USERID. The data type of this property is String. The maximum length is 255 bytes.

A Java empty string ("") is valid for the clientUser value, but the Java `null` value is not valid.

clientWorkstation
Specifies the host name of the computer on which the application that is using the connection is running. This value is stored in Db2 special register CURRENT CLIENT_WRKSTNNAME. The data type of this property is . The maximum length is 255 bytes.

Starting with version 3.68 or 4.18 of the IBM Data Server Driver for JDBC and SQLJ, if clientWorkstation is set to 'NODEFAULT', no value is sent to the data server.

concurrentAccessResolution
Specifies whether the IBM Data Server Driver for JDBC and SQLJ requests that a read transaction can access a committed and consistent image of rows that are incompatibly locked by write transactions, if the data source supports accessing currently committed data, and the application isolation level is cursor stability (CS) or read stability (RS). This option has the same effect as the Db2 CONCURRENTACCESSRESOLUTION bind option. Possible values are:

DB2BaseDataSource.-
CONCURRENTACCESS_USE_CURRENTLY_COMMITTED (1)
The IBM Data Server Driver for JDBC and SQLJ requests that:

- Read transactions access the currently committed data when the data is being updated or deleted.
- Read transactions skip rows that are being inserted.

DB2BaseDataSource.CONCURRENTACCESS_WAIT_FOR_OUTCOME (2)
The IBM Data Server Driver for JDBC and SQLJ requests that:

- Read transactions wait for a commit or rollback operation when they encounter data that is being updated or deleted.
- Read transactions do not skip rows that are being inserted.

DB2BaseDataSource.CONCURRENTACCESS_NOT_SET (0)
Enables the data server's default behavior for read transactions when lock contention occurs. This is the default value.

currentDegree
Specifies the degree of parallelism for the execution of queries that are dynamically prepared. The type of this property is . The currentDegree value is used to set the CURRENT DEGREE special register on the data source. If currentDegree is not set, no value is passed to the data source.

currentExplainMode
Specifies the value for the CURRENT EXPLAIN MODE special register. The CURRENT EXPLAIN MODE special register enables and disables the Explain facility. The data type of this property is String. The maximum length is 254 bytes. This property applies only to connections to data sources that support the CURRENT EXPLAIN MODE special register.

currentFunctionPath
Specifies the SQL path that is used to resolve unqualified data type names and function names in SQL statements that are in JDBC programs. The data type of this property is . For a Db2 on Linux, UNIX, and Windows systems server, the maximum length is 254 bytes. For a Db2 for z/OS server, the maximum length is 2048 bytes. The value is a comma-separated list of schema names. Those names can be ordinary or delimited identifiers.

currentMaintainedTableTypesForOptimization
Specifies a value that identifies the types of objects that can be considered when the data source optimizes the processing of dynamic SQL queries. This register contains a keyword representing table types. The data type of this property is .

Possible values of currentMaintainedTableTypesForOptimization are:

ALL
Indicates that all materialized query tables will be considered.

NONE
Indicates that no materialized query tables will be considered.

SYSTEM
Indicates that only system-maintained materialized query tables that are refresh deferred will be considered.

USER
Indicates that only user-maintained materialized query tables that are refresh deferred will be considered.

currentPackagePath
Specifies a comma-separated list of collections on the server. The data server searches these collections for JDBC and SQLJ packages.

The precedence rules for the currentPackagePath and currentPackageSet properties follow the precedence rules for the CURRENT PACKAGESET and CURRENT PACKAGE PATH special registers.

currentPackageSet
Specifies the collection ID to search for JDBC and SQLJ packages. The data type of this property is . The default is NULLID for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, if a value for currentPackageSet is not specified, the property value is not set. If currentPackageSet is set, its value overrides the value of jdbcCollection.

Multiple instances of the IBM Data Server Driver for JDBC and SQLJ can be installed at a data server by running the DB2Binder utility multiple times. The DB2binder utility includes a -collection option

that lets the installer specify the collection ID for each IBM Data Server Driver for JDBC and SQLJ instance. To choose an instance of the IBM Data Server Driver for JDBC and SQLJ for a connection, you specify a currentPackageSet value that matches the collection ID for one of the IBM Data Server Driver for JDBC and SQLJ instances.

The precedence rules for the currentPackagePath and currentPackageSet properties follow the precedence rules for the CURRENT PACKAGESET and CURRENT PACKAGE PATH special registers.

currentRefreshAge
Specifies a timestamp duration value that is the maximum duration since a REFRESH TABLE statement was processed on a system-maintained REFRESH DEFERRED materialized query table such that the materialized query table can be used to optimize the processing of a query. This property affects dynamic statement cache matching. The data type of this property is long.

currentSchema
Specifies the default schema name that is used to qualify unqualified database objects in dynamically prepared SQL statements. The value of this property sets the value in the CURRENT SCHEMA special register on the data server. The schema name is case-sensitive, and must be specified in uppercase characters.

cursorSensitivity
Specifies whether the `java.sql.ResultSet.TYPE_SCROLL_SENSITIVE` value for a JDBC `ResultSet` maps to the SENSITIVE DYNAMIC attribute, the SENSITIVE STATIC attribute, or the ASENSITIVE attribute for the underlying database cursor. The data type of this property is int. Possible values are `TYPE_SCROLL_SENSITIVE_STATIC` (0), `TYPE_SCROLL_SENSITIVE_DYNAMIC` (1), or `TYPE_SCROLL_ASENSITIVE` (2). The default is `TYPE_SCROLL_SENSITIVE_STATIC`.

If the data source does not support sensitive dynamic scrollable cursors, and `TYPE_SCROLL_SENSITIVE_DYNAMIC` is requested, the JDBC driver accumulates a warning and maps the sensitivity to SENSITIVE STATIC. For Db2 for IBM i data servers, which do not support sensitive static cursors, `java.sql.ResultSet.TYPE_SCROLL_SENSITIVE` always maps to SENSITIVE DYNAMIC.

dateFormat
Specifies:

- The format in which the argument of the `PreparedStatement.setString` method against a DATE column must be specified.
- The format in which the result of the `ResultSet.getString` or `CallableStatement.getString` method against a DATE column is returned.

The data type of dateFormat is int.

Possible values of dateFormat are:

Constant	Integer value	Format
`com.ibm.db2.jcc.DB2BaseDataSource.ISO`	1	*yyyy-mm-dd*
`com.ibm.db2.jcc.DB2BaseDataSource.USA`	2	*mm/dd/yyyy*
`com.ibm.db2.jcc.DB2BaseDataSource.EUR`	3	*dd.mm.yyyy*
`com.ibm.db2.jcc.DB2BaseDataSource.JIS`	4	*yyyy-mm-dd*

The default is `com.ibm.db2.jcc.DB2BaseDataSource.ISO`.

decimalRoundingMode
Specifies the rounding mode for assignment to decimal floating-point variables or DECFLOAT columns on Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems data servers.

Possible values are:

DB2BaseDataSource.ROUND_DOWN (1)
Rounds the value towards 0 (truncation). The discarded digits are ignored.

DB2BaseDataSource.ROUND_CEILING (2)
Rounds the value towards positive infinity. If all of the discarded digits are zero or if the sign is negative the result is unchanged other than the removal of the discarded digits. Otherwise, the result coefficient is incremented by 1.

DB2BaseDataSource.ROUND_HALF_EVEN (3)
Rounds the value to the nearest value; if the values are equidistant, rounds the value so that the final digit is even. If the discarded digits represents greater than half (0.5) of the value of one in the next left position then the result coefficient is incremented by 1. If they represent less than half, then the result coefficient is not adjusted (that is, the discarded digits are ignored). Otherwise the result coefficient is unaltered if its rightmost digit is even, or is incremented by 1 if its rightmost digit is odd (to make an even digit).

DB2BaseDataSource.ROUND_HALF_UP (4)
Rounds the value to the nearest value; if the values are equidistant, rounds the value away from zero. If the discarded digits represent greater than or equal to half (0.5) of the value of one in the next left position then the result coefficient is incremented by 1. Otherwise the discarded digits are ignored.

DB2BaseDataSource.ROUND_FLOOR (6)
Rounds the value towards negative infinity. If all of the discarded digits are zero or if the sign is positive the result is unchanged other than the removal of discarded digits. Otherwise, the sign is negative and the result coefficient is incremented by 1.

DB2BaseDataSource.ROUND_UNSET (-2147483647)
No rounding mode was explicitly set. The IBM Data Server Driver for JDBC and SQLJ does not use the decimalRoundingMode to set the rounding mode on the data server. The rounding mode is ROUND_HALF_EVEN.

If you explicitly set the decimalRoundingMode value, that value updates the CURRENT DECFLOAT ROUNDING MODE special register value on a Db2 for z/OS data server.

If you explicitly set the decimalRoundingMode value, that value does not update the CURRENT DECFLOAT ROUNDING MODE special register value on a Db2 on Linux, UNIX, and Windows systems data server. If the value to which you set decimalRoundingMode is not the same as the value of the CURRENT DECFLOAT ROUNDING MODE special register, an `Exception` is thrown. To change the data server value, you need to set that value with the decflt_rounding database configuration parameter.

decimalRoundingMode does not affect decimal value assignments. The IBM Data Server Driver for JDBC and SQLJ always rounds decimal values down.

enableExtendedDescribe
Specifies whether the IBM Data Server Driver for JDBC and SQLJ requests extended describe information from the data server when it prepares a statement.

Extended describe information provides:

- Additional descriptive information for a cursor or a result set
- Information about whether a column:
  - Can be updated
  - Is a primary key or a preferred candidate key member
  - Is an expression or a table column
  - is a generated column or a table column
- The fully qualified view or table name
- The fully qualified column name

Possible values are:

DB2BaseDataSource.NOT_SET (0)
The IBM Data Server Driver for JDBC and SQLJ requests extended describe information. This is the default.

DB2BaseDataSource.YES (1)
The IBM Data Server Driver for JDBC and SQLJ requests extended describe information.

DB2BaseDataSource.NO (2)
The IBM Data Server Driver for JDBC and SQLJ does not request extended describe information.

Setting enableExtendedDescribe to `DB2BaseDataSource.NO` can result in a performance benefit because it avoids the extra processing that the driver must do to provide the additional information. However, if you specify this is option, some methods throw an exception or return unexpected results. The following table lists the behavior of methods when enableExtendedDescribe is set to `DB2BaseDataSource.NO`.

Method	Result when extended describe is off
Connection.findAutoGeneratedKeysColumn	Returns an array of empty strings ("")
DB2ResultSetMetaData.getDBTemporalColumnType	Returns -1
ResultSet.getMetaData on the ResultSet object that is returned by PreparedStatement.getGeneratedKeys	Returns null
ResultSet.insertRow, ResultSet.deleteRow, ResultSet.updateRow	SQLException with error code -4474, SQLSTATE 42808 (column not updatable)
ResultSet.updateXXX methods	SQLException with error code -4474, SQLSTATE 42808 (column not updatable)
ResultSetMetaData.getTableName, ResultSetMetaData.getSchemaName, ResultSetMetaData.getColumnName	Returns an empty string ("")
ResultSetMetaData.isAutoIncrement	Returns `false`

enableExtendedIndicators
Specifies whether support for extended indicators is enabled in the IBM Data Server Driver for JDBC and SQLJ. Possible values are:

DB2BaseDataSource.YES (1)
Support for extended indicators is enabled in the IBM Data Server Driver for JDBC and SQLJ.

DB2BaseDataSource.NO (2)
Support for extended indicators is disabled in the IBM Data Server Driver for JDBC and SQLJ.

DB2BaseDataSource.NOT_SET (0)
Support for extended indicators is enabled in the IBM Data Server Driver for JDBC and SQLJ. This is the default value.

enableRowsetSupport
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses multiple-row FETCH for forward-only cursors or scrollable cursors, if the data server supports multiple-row FETCH. The data type of this property is int.

For connections to Db2 for z/OS, when enableRowsetSupport is set, its value overrides the useRowsetCursor property value.

Possible values are:

DB2BaseDataSource.YES (1)
Specifies that:

- For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS, multiple-row FETCH is used for scrollable cursors and forward-only cursors, if the data server supports multiple-row FETCH.

- For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 on Linux, UNIX, and Windows systems, multiple-row fetch is used for scrollable cursors, if the data server supports multiple-row FETCH.

DB2BaseDataSource.NO (2)
Specifies that multiple-row fetch is not used.

DB2BaseDataSource.NOT_SET (0)
Specifies that if the enableRowsetSupport property is not set:

- For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS, multiple-row fetch is not used.
- For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS, multiple-row fetch is used if useRowsetCursor is set to `true`.
- For connections to Db2 on Linux, UNIX, and Windows systems, multiple row fetch is used for scrollable cursors, if the data server supports multiple-row FETCH.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS, multiple-row fetch is not compatible with progressive streaming. Therefore, if progressive streaming is used for a FETCH operation, multiple-row FETCH is not used.

enableTimeoutOnCursor
For `DatabaseMetaData` or `ResultSet` methods that use `Statement` objects in their implementations, specifies whether the commandTimeout and queryTimeoutInterruptProcessingMode property values control the timeout behavior for those `Statement` objects.

Examples of methods that use `Statement` objects in their implementations are:

- ResultSet.updateRow
- ResultSet.insertRow
- ResultSet.deleteRow
- DatabaseMetaData.getProcedures
- DatabaseMetaData.getTables
- DatabaseMetaData.getColumns

The data type of this property is int. The possible values are:

com.ibm.db2.jcc.DB2BaseDataSource.YES (1) or com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0)
A `Statement` object that is used in the implementation of a `DatabaseMetaData` or `ResultSet` method is controlled by the commandTimeout and queryTimeoutInterruptProcessingMode properties. This behavior is the default behavior.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2)
A `Statement` object that is used in the implementation of a `DatabaseMetaData` or `ResultSet` method is not controlled by the commandTimeout and queryTimeoutInterruptProcessingMode properties.

encryptionAlgorithm
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses 56-bit DES (weak) encryption or 256-bit AES (strong) encryption. The data type of this property is int. Possible values are:

1
The driver uses 56-bit DES encryption.

2
The driver uses 256-bit AES encryption, if the data server supports it. 256-bit AES encryption is available for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

For AES encryption, you need an unrestricted policy file for JCE. That file is available at the following location:

```
https://www.ibm.com/marketing/iwm/iwm/web/preLogin.do?source=jcesdk
```

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default encryption is 256-bit AES encryption (2).

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default encryption algorithm is 56-bit DES encryption (1).

encryptionAlgorithm can be specified only if the securityMechanism or db2.jcc.securityMechanism value is ENCRYPTED_PASSWORD_SECURITY (7) or ENCRYPTED_USER_AND_PASSWORD_SECURITY (9).

fullyMaterializeInputStreams
Indicates whether streams are fully materialized before they are sent from the client to a data source. The data type of this property is boolean. The default is `false`.

If the value of `fullyMaterializeInputStreams` is `true`, the JDBC driver fully materialized the streams before sending them to the server.

gssCredential
For a data source that uses Kerberos security, specifies a delegated credential that is passed from another principal. The data type of this property is org.ietf.jgss.GSSCredential. Delegated credentials are used in multi-tier environments, such as when a client connects to WebSphere Application Server, which, in turn, connects to the data source. You obtain a value for this property from the client, by invoking the `GSSContext.getDelegCred` method. `GSSContext` is part of the IBM Java Generic Security Service (GSS) API. If you set this property, you also need to set the Mechanism and KerberosServerPrincipal properties.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

For more information on using Kerberos security with the IBM Data Server Driver for JDBC and SQLJ, see "Using Kerberos security under the IBM Data Server Driver for JDBC and SQLJ".

kerberosServerPrincipal
For a data source that uses Kerberos security, specifies the name that is used for the data source when it is registered with the Kerberos Key Distribution Center (KDC). The data type of this property is .

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

MAXBLKEXT
Specifies the maximum number of extra blocks that the DRDA client can receive from the data server without further prompting. The data type of this property is int.

Possible values are:

-1
The data server determines the maximum number of extra blocks that the client can receive. -1 is the default.

0
The client receives no extra blocks.

n
The maximum number of extra blocks that the client can receive. *n* is an integer that is greater than or equal to 1 and less than or equal to 100.

If the MAXBLKEXT value is also set through the `DB2ResultSet.setMAXBLKEXT` or `DB2Statement.setMAXBLKEXT` method, the setting through the method overrides the value of the MAXBLKEXT `Connection` or `DataSource` property.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

pdqProperties
Specifies properties that control the interaction between the IBM Data Server Driver for JDBC and SQLJ and the client optimization feature of pureQuery.

The data type of this property is .

Set the pdqProperties property **only** if you are using the client optimization feature of pureQuery. See the Integrated Data Management Information Center for information about valid values for pdqProperties.

queryPrefetch
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses query prefetch behavior for retrieving rows from a Db2 table. Use of query prefetch can improve performance when an application retrieves large result sets. Query prefetch is not used when an application retrieves LOB or XML data, or when the cursor that is used for data retrieval is not a forward-only cursor.

The data type of queryPrefetch is boolean. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

Possible values are:

true
Specifies that the IBM Data Server Driver for JDBC and SQLJ can use query prefetch when it retrieves rows from a table.

false
Specifies that the IBM Data Server Driver for JDBC and SQLJ does not use query prefetch when it retrieves rows from a table. `false` is the default.

readOnly
Specifies whether the connection is read-only. The data type of this property is boolean. The default is `false`.

resultSetHoldabilityForCatalogQueries
Specifies whether cursors for queries that are executed on behalf of `DatabaseMetaData` methods remain open after a commit operation. The data type of this property is int.

When an application executes `DatabaseMetaData` methods, the IBM Data Server Driver for JDBC and SQLJ executes queries against the catalog of the target data source. By default, the holdability of those cursors is the same as the holdability of application cursors. To use different holdability for catalog queries, use the resultSetHoldabilityForCatalogQueries property. Possible values are:

DB2BaseDataSource.HOLD_CURSORS_OVER_COMMIT (1)
Leave cursors for catalog queries open after a commit operation, regardless of the resultSetHoldability setting.

DB2BaseDataSource.CLOSE_CURSORS_AT_COMMIT (2)
Close cursors for catalog queries after a commit operation, regardless of the resultSetHoldability setting.

DB2BaseDataSource.NOT_SET (0)
Use the resultSetHoldability setting for catalog queries. This is the default value.

returnAlias
Specifies whether the JDBC driver returns rows for table aliases and synonyms for `DatabaseMetaData` methods that return table information, such as `getTables`. The data type of returnAlias is int. Possible values are:

0
Do not return rows for aliases or synonyms of tables in output from `DatabaseMetaData` methods that return table information.

1
For tables that have aliases or synonyms, return rows for aliases and synonyms of those tables, as well as rows for the tables, in output from `DatabaseMetaData` methods that return table information. This is the default.

sslClientHostnameValidation
Specifies whether the IBM Data Server Driver for JDBC and SQLJ performs client host name validation when establishing a connection to a data server that uses transport layer security (TLS). Host name validation is performed according to the standard that is specified in IETF RFC 6125.

sslClientHostnameValidation can have one of the following values:

BASIC
Specifies that host name validation is enabled. During the TLS handshake, when the data server sends its certificate to the driver, the driver checks whether the host name or its corresponding IP address in the certificate matches the host name or corresponding IP address that the application provides to the driver.

OFF
Specifies that host name validation is disabled. This is the default.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS and to Db2 on Linux, UNIX, and Windows systems .

statementConcentrator
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses the data source's statement concentrator functionality. The statement concentrator is the ability to bypass preparation of a statement when it is the same as a statement in the dynamic statement cache, except for literal values. Statement concentrator functionality applies only to SQL statements that have literals but no parameter markers. Possible values are:

DB2BaseDataSource.STATEMENT_CONCENTRATOR_OFF (1)
The IBM Data Server Driver for JDBC and SQLJ does not use the data source's statement concentrator functionality.

DB2BaseDataSource.STATEMENT_CONCENTRATOR_WITH_LITERALS (2)
The IBM Data Server Driver for JDBC and SQLJ uses the data source's statement concentrator functionality.

DB2BaseDataSource.STATEMENT_CONCENTRATOR_NOT_SET (0)
Enables the data server's default behavior for statement concentrator functionality. This is the default value.

For Db2 on Linux, UNIX, and Windows systems data sources that support statement concentrator functionality, the functionality is used if the STMT_CONC configuration parameter is set to ON at the data source. Otherwise, statement concentrator functionality is not used.

For Db2 for z/OS data sources that support statement concentrator functionality, the functionality is not used if statementConcentrator is not set.

streamBufferSize
Specifies the size, in bytes, of the JDBC driver buffers for chunking LOB or XML data. The JDBC driver uses the streamBufferSize value whether or not it uses progressive streaming. The data type of streamBufferSize is int. The default is 1048576.

If the JDBC driver uses progressive streaming, LOB or XML data is materialized if it fits in the buffers, and the driver does not use the fullyMaterializeLobData property.

Db2 for z/OS Version 9.1 and later supports progressive streaming for LOBs and XML objects. Db2 on Linux, UNIX, and Windows systems Version 9.5 and later, and IBM Informix Version 11.50 and later support progressive streaming for LOBs.

supportsAsynchronousXARollback
Specifies whether the IBM Data Server Driver for JDBC and SQLJ supports asynchronous XA rollback operations. The data type of this property is int. The default is `DB2BaseDataSource.NO` (2). If the application runs against a BEA WebLogic Server application server, set supportsAsynchronousXARollback to `DB2BaseDataSource.YES` (1).

sysSchema
Specifies the schema of the shadow catalog tables or views that are searched when an application invokes a `DatabaseMetaData` method. The sysSchema property was formerly called cliSchema.

timeFormat
Specifies:

- The format in which the argument of the `PreparedStatement.setString` method against a TIME column must be specified.

- The format in which the result of the `ResultSet.getString` or `CallableStatement.getString` method against a TIME column is returned.

The data type of timeFormat is int.

Possible values of timeFormat are:

Constant	Integer value	Format
`com.ibm.db2.jcc.DB2BaseDataSource.ISO`	1	*hh:mm:ss*
`com.ibm.db2.jcc.DB2BaseDataSource.USA`	2	*hh:mm* am or *hh:mm* pm
`com.ibm.db2.jcc.DB2BaseDataSource.EUR`	3	*hh.mm.ss*
`com.ibm.db2.jcc.DB2BaseDataSource.JIS`	4	*hh:mm:ss*

The default is `com.ibm.db2.jcc.DB2BaseDataSource.ISO`.

timestampOutputType
Specifies whether the IBM Data Server Driver for JDBC and SQLJ returns a `java.sql.Timestamp` object or a `com.ibm.db2.jcc.DBTimestamp` when the standard JDBC interfaces `ResultSet.getTimestamp`, `CallableStatement.getTimestamp`, `ResultSet.getObject`, or `CallableStatement.getObject` are called to return timestamp information.

Possible values are:

DB2BaseDataSource.JDBC_TIMESTAMP (1)
The IBM Data Server Driver for JDBC and SQLJ returns `java.sql.Timestamp` objects from `ResultSet.getTimestamp`, `CallableStatement.getTimestamp`, `ResultSet.getObject`, or `CallableStatement.getObject` calls.

DB2BaseDataSource.JCC_DBTIMESTAMP (2)
The IBM Data Server Driver for JDBC and SQLJ returns `com.ibm.db2.jcc.DBTimestamp` objects from `ResultSet.getTimestamp`, `CallableStatement.getTimestamp`, `ResultSet.getObject`, or `CallableStatement.getObject` calls.

DB2BaseDataSource.NOT_SET (0)
This is the default behavior.

The behavior is the same as the behavior for DB2BaseDataSource.JDBC_TIMESTAMP.

useCachedCursor
Specifies whether the underlying cursor for `PreparedStatement` objects is cached and reused on subsequent executions of a `PreparedStatement` object. The data type of useCachedCursor is boolean.

If useCachedCursor is set to `true`, the cursor for `PreparedStatement` objects is cached, which can improve performance.

Set useCachedCursor to `false` if `PreparedStatement` objects access tables whose column types or lengths change between executions of those `PreparedStatement` objects.

The default for useCachedCursor is:

- `false`, if the data server is Db2 on Linux, UNIX, and Windows systems, and the driver is at one of the following levels:
  - Version 3.67 or 4.17, or later
  - Version 3.64
- `true`, if the data server and driver version are one of the following combinations:
  - For a Db2 for z/OS data server, any version of the driver other than the versions for which useCachedCursor is false

If the driver version is 3.67 or 4.17, or later, or 3.64 , and the deferPrepares property is set to true, the driver behaves as if useCachedCursor is set to false, regardless of the useCachedCursor setting.

The useCachedCursor property is deprecated in version 3.69 or 4.19 of the driver. You can achieve better performance when the property is not set by the application. If you need the older driver behavior, explicitly set the property to `true` or `false`.

useClientSideLicenseFirst
Specifies whether the IBM Data Server Driver for JDBC and SQLJ checks the client-side license before the server-side license for permission to access the data server.

useClientSideLicenseFirst can have one of the following values:

`DB2BaseDataSource.YES` (1)
1
Check whether a client-side license exists, and if so, use it to validate the connection. If a client-side license does not exist, check for a server-side license. If neither license exists, the driver throws a LicenseException.

`DB2BaseDataSource.NO` (2) or DB2BaseDataSource.NOT_SET (0)
Check whether a server-side license exists, and if so, use it to validate the connection. If a server-side license does not exist, check for a client-side license. If neither license exists, the driver throws a LicenseException. This is the default behavior.

useClientSideLicenseFirst applies to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS, Db2 for IBM i, and Db2 on Cloud, and to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

useIdentityValLocalForAutoGeneratedKeys
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses only the SQL built-in function IDENTITY_VAL_LOCAL to determine automatically generated key values. The data type of this property is boolean. Possible values are:

true
Specifies that the IBM Data Server Driver for JDBC and SQLJ always uses the SQL built-in function IDENTITY_VAL_LOCAL to determine automatically generated key values. The driver uses IDENTITY_VAL_LOCAL even if it is possible to use SELECT FROM INSERT.

Specify `true` if the target data server supports SELECT FROM INSERT, but the target objects do not. For example, SELECT FROM INSERT is not valid for a table on which a trigger is defined.

false
Specifies that the IBM Data Server Driver for JDBC and SQLJ determines whether to use SELECT FROM INSERT or IDENTITY_VAL_LOCAL to determine automatically generated keys. `false` is the default.

useJDBC4ColumnNameAndLabelSemantics
Specifies how the IBM Data Server Driver for JDBC and SQLJ handles column labels in `ResultSetMetaData.getColumnName`, `ResultSetMetaData.getColumnLabel`, and `ResultSet.findColumn` method calls.

Possible values are:

DB2BaseDataSource.YES (1)
The IBM Data Server Driver for JDBC and SQLJ uses the following rules, which conform to the JDBC 4.0 specification, to determine the value that `ResultSetMetaData.getColumnName`, `ResultSetMetaData.getColumnLabel`, and `ResultSet.findColumn` return:

- The column name that is returned by `ResultSetMetaData.getColumnName` is its name from the database.
- The column label that is returned by `ResultSetMetaData.getColumnLabel` is the label that is specified with the SQL AS clause. If the SQL AS clause is not specified, the label is the name of the column.

- `ResultSet.findColumn` takes the label for the column, as specified with the SQL AS clause, as input. If the SQL AS clause was not specified, the label is the column name.
- The IBM Data Server Driver for JDBC and SQLJ does not use a column label that is assigned by the SQL LABEL ON statement.

These rules apply to IBM Data Server Driver for JDBC and SQLJ version 3.50 and later, for connections to the following database systems:

- Db2 for z/OS Version 8 or later
- Db2 on Linux, UNIX, and Windows systems Version 8.1 or later
- Db2 for IBM i V5R3 or later

For earlier versions of the driver or the database systems, the rules for a useJDBC4ColumnNameAndLabelSemantics value of DB2BaseDataSource.NO apply, even if useJDBC4ColumnNameAndLabelSemantics is set to DB2BaseDataSource.YES.

DB2BaseDataSource.NO (2)

The IBM Data Server Driver for JDBC and SQLJ uses the following rules to determine the values that `ResultSetMetaData.getColumnName`, `ResultSetMetaData.getColumnLabel`, and `ResultSet.findColumn` return:

If the data source does not support the LABEL ON statement, or the source column is not defined with the LABEL ON statement:

- The value that is returned by `ResultSetMetaData.getColumnName` is its name from the database, if no SQL AS clause is specified. If the SQL AS clause is specified, the value that is returned is the column label.
- The value that is returned by `ResultSetMetaData.getColumnLabel` is the label that is specified with the SQL AS clause. If the SQL AS clause is not specified, the value that is returned is the name of the column.
- `ResultSet.findColumn` takes the column name as input.

If the source column is defined with the LABEL ON statement:

- The value that is returned by `ResultSetMetaData.getColumnName` is the column name from the database, if no SQL AS clause is specified. If the SQL AS clause is specified, the value that is returned is the column label that is specified in the AS clause.
- The value that is returned by `ResultSetMetaData.getColumnLabel` is the label that is specified in the LABEL ON statement.
- `ResultSet.findColumn` takes the column name as input.

These rules conform to the behavior of the IBM Data Server Driver for JDBC and SQLJ before Version 3.50.

DB2BaseDataSource.NOT_SET (0)

This is the default behavior.

For the IBM Data Server Driver for JDBC and SQLJ version 3.50 and earlier, the default behavior for useJDBC4ColumnNameAndLabelSemantics is the same as the behavior for DB2BaseDataSource.NO.

For the IBM Data Server Driver for JDBC and SQLJ version 4.0 and later:

- The default behavior for useJDBC4ColumnNameAndLabelSemantics is the same as the behavior for DB2BaseDataSource.YES, for connections to the following database systems:
  - Db2 for z/OS Version 8 or later
  - Db2 on Linux, UNIX, and Windows systems Version 8.1 or later
  - Db2 for IBM i V5R3 or later
- For connections to earlier versions of these database systems, the default behavior for useJDBC4ColumnNameAndLabelSemantics is DB2BaseDataSource.NO.

xmlFormat
Specifies the format that is used to retrieve XML data from the data server. The XML format cannot be modified after a connection is established. Possible values are:

com.ibm.db2.jcc.DB2BaseDataSource.XML_FORMAT_NOT_SET (-Integer.MAX_VALUE)
Specifies that the default XML format is used. The default is textual XML format.

com.ibm.db2.jcc.DB2BaseDataSource.XML_FORMAT_TEXTUAL (0)
Specifies that the XML textual format is used.

com.ibm.db2.jcc.DB2BaseDataSource.XML_FORMAT_BINARY (1)
Specifies that the binary XML format is used.

When binary XML is used, the XML data that is passed to the IBM Data Server Driver for JDBC and SQLJ cannot refer to external entities, internal entities, or internal DTDs. External DTDs are supported only if those DTDs were previously registered in the data source.

com.ibm.db2.jcc.DB2ConnectionPoolDataSource.maxStatements
Controls an internal statement cache that is associated with a `PooledConnection`. The data type of this property is int. Possible values are:

positive integer
Enables the internal statement cache for a `PooledConnection`, and specifies the number of statements that the IBM Data Server Driver for JDBC and SQLJ keeps open in the cache.

0 or negative integer
Disables internal statement caching for the `PooledConnection`. 0 is the default.

maxStatements controls the internal statement cache that is associated with a `PooledConnection` only when the `PooledConnection` object is created. maxStatements has no effect on caching in an already existing `PooledConnection` object.

maxStatements applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, and toIBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

com.ibm.db2.jcc.DB2ConnectionPool.acquireIncrement
Specifies the number of new connections that are to be acquired when all connections in a connection pool are exhausted. The data type of this property is int. The default is 1.

com.ibm.db2.jcc.DB2ConnectionPool.acquireRetryAttempts
For a new connection, specifies the number of retries that are to be performed if the initial connection attempt fails. The data type of this property is int. The default is 1 retry.

com.ibm.db2.jcc.DB2ConnectionPool.acquireRetryDelay
For a new connection, specifies the amount of time in seconds to wait between retries if the initial connection attempt fails. The data type of this property is int. The default is 1.

com.ibm.db2.jcc.DB2ConnectionPool.autoCommit
Specifies whether autocommit is enabled for all SQL update operations during the existence of a pooled connection. The data type of this property is Boolean. Possible values are:

true
Autocommit is enabled during the existence of the pooled connection.

false
Autocommit is disabled during the existence of the pooled connection. `false` is the default.

com.ibm.db2.jcc.DB2ConnectionPool.connectionTimeout
Specifies the amount of time in seconds to wait for a pooled connection to open. The data type of this property is int. The default is 0, which means that there is no time limit.

com.ibm.db2.jcc.DB2ConnectionPool.databaseName
Specifies the name of the data server. This name is the *database* portion of the connection URL. The data type of this property is . The default is the local site.

com.ibm.db2.jcc.DB2ConnectionPool.driverType
Specifies the type of IBM Data Server Driver for JDBC and SQLJ connectivity to the data server. Possible values are 2 or 4. The data type of this property is int. The default is 2.

com.ibm.db2.jcc.DB2ConnectionPool.initialPoolSize
Specifies the number of connections that should be created initially in the connection pool. The data type of this property is int.

com.ibm.db2.jcc.DB2ConnectionPool.loginTimeout
Specifies the maximum time in seconds to wait for a pooled connection to a data server. After the number of seconds that are specified by loginTimeout have elapsed, the driver closes the connection to the data server. The data type of this property is int. The default is 0. A value of 0 means that the timeout value is the default system timeout value.

com.ibm.db2.jcc.DB2ConnectionPool.logWriter
Specifies the character output stream to which all logging and trace messages for the DB2Pool object are printed. The data type of this property is java.io.PrinterWriter. The default value is null, which means that no logging or tracing for the DB2ConnectionPool object is done.

com.ibm.db2.jcc.DB2ConnectionPool.maxIdleTime
Specifies how many seconds connections in the connection pool remain unused before they are released. The data type of this property is int.

com.ibm.db2.jcc.DB2ConnectionPool.maxPoolSize
Specifies the maximum number of connections in the connection pool. The data type of this property is int. The default value is no maximum.

com.ibm.db2.jcc.DB2ConnectionPool.password
Specifies the password for the DB2ConnectionPool object. The data type of this property is .

com.ibm.db2.jcc.DB2ConnectionPool.poolLoggingFrequency
Specifies how often, in seconds, trace data from the connection pool is written to the log. The data type of this property is int. The default is 0, which means that trace data is not written to the log.

com.ibm.db2.jcc.DB2ConnectionPool.portNumber
Specifies the TCP/IP server port number that is assigned to the data server to which the application is connecting. The data type of this property is int. The value can be any integer greater than or equal to 0 and less than or equal to 65535. The default is 446.

com.ibm.db2.jcc.DB2ConnectionPool.preferredTestQuery
Specifies an SQL query that is used to test pooled connections for connectivity to the data server. The data type of this property is . The default is 'SELECT CURRENT DATE FROM SYSIBM.SYSDUMMY1'.

com.ibm.db2.jcc.DB2ConnectionPool.serverName
Specifies the domain name or IP address of the data server to which the application is connecting. The data type of this property is . There is no default.

com.ibm.db2.jcc.DB2ConnectionPool.testConnectionOnCheckin
Specifies whether to enable automatic connection checking when an application releases its connection to the connection pool. The data type of this property is Boolean. Possible values are:

true
Automatic connection checking is enabled.

false
Automatic connection checking is disabled. `false` is the default.

com.ibm.db2.jcc.DB2ConnectionPool.testConnectionOnCheckout
Specifies whether to enable automatic connection checking when an application obtains its connection to the connection pool. The data type of this property is Boolean. Possible values are:

true
Automatic connection checking is enabled.

false
Automatic connection checking is disabled. `false` is the default.

com.ibm.db2.jcc.DB2ConnectionPool.traceFile
Specifies the name of a file into which the IBM Data Server Driver for JDBC and SQLJ writes trace information. The data type of this property is String. The traceFile property is an alternative to the logWriter property for directing the output trace stream to a file.

com.ibm.db2.jcc.DB2ConnectionPool.traceLevel
Specifies what to trace.

You can specify one or more of the following traces with the traceLevel parameter:

- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_NONE (X'00')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTION_CALLS (X'01')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_STATEMENT_CALLS (X'02')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_CALLS (X'04')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRIVER_CONFIGURATION (X'10')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTS (X'20')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS (X'40')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_META_DATA (X'80')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_PARAMETER_META_DATA (X'100')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DIAGNOSTICS (X'200')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SQLJ (X'400')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_XA_CALLS (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity for Db2 on Linux, UNIX, and Windows systems only) (X'800')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_META_CALLS (X'2000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DATASOURCE_CALLS (X'4000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_LARGE_OBJECT_CALLS (X'8000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_T2ZOS (X'10000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSTEM_MONITOR (X'20000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_TRACEPOINTS (X'40000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSPLEX (X'80000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL (X'FFFFFFFF')

To specify more than one trace, use one of these techniques:

- Use bitwise OR (|) operators with two or more trace values. For example, to trace DRDA flows and connection calls, specify this value for traceLevel:

```
TRACE_DRDA_FLOWS|TRACE_CONNECTION_CALLS
```

- Use a bitwise complement (tilde (~)) operator with a trace value to specify all except a certain trace. For example, to trace everything except DRDA flows, specify this value for traceLevel:

```
 ~TRACE_DRDA_FLOWS
```

com.ibm.db2.jcc.DB2ConnectionPool.user
The user ID to use for establishing connections. The data type of this property is String.

Related concepts

“Examples of ResultSetMetaData.getColumnName and ResultSetMetaData.getColumnLabel values” on page 501
For the IBM Data Server Driver for JDBC and SQLJ version 4.0 and later, the default behavior of ResultSetMetaData.getColumnName and ResultSetMetaData.getColumnLabel differs from the default behavior for earlier JDBC drivers. You can use the useJDBC4ColumnNameAndLabelSemantics property to change this behavior.

Related reference

Setting properties locally for individual connections that use the IBM Data Server Driver for JDBC and SQLJ

Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS and IBM Informix

Some of the IBM Data Server Driver for JDBC and SQLJ properties apply to IBM Informix and Db2 for z/OS database servers.

Properties that apply to IBM Informix and Db2 for z/OS are:

enableConnectionConcentrator
Indicates whether the connection concentrator function of the IBM Data Server Driver for JDBC and SQLJ is enabled.

The data type of enableConnectionConcentrator is boolean. The default is `false`.

enableConnectionConcentrator applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

The following table shows the interaction between the enableConnectionConcentrator and enableSysplexWLB property settings:

Table 39. Result of enableConnectionConcentrator and enableSysplexWLB settings

enableConnectionConcentrator setting	enableSysplexWLB setting	Result
false	false	The connection of the application to the data server is associated to one transport for the life of that connection.
false	true	The connection of the application to the data server chooses a transport based on the weights that are returned by the data server. A transport is chosen at every transaction boundary. This action balances the load on different Db2 data sharing members.
true	false	Several application connections can share the same transport for executing their transactions. The switching of the transport between connections occurs at each transaction boundary. Because many connections share one transport to the data server, fewer resources can be used on the data server.
true	true	The connection of the application to the data server chooses a transport based on the weights that are returned by the data server. A transport is chosen at every transaction boundary. This action balances the load on different Db2 data sharing members. This is the same behavior as the behavior when enableConnectionConcentrator is false and enableSysplexWLB is true.

keepDynamic
Specifies whether the data source keeps already prepared dynamic SQL statements in the dynamic statement cache after the point of commit or rollback so that those prepared statements can be

reused. The data type of this property is int. Valid values are DB2BaseDataSource.YES (1) and DB2BaseDataSource.NO (2).

If the keepDynamic property is not specified, the keepDynamic value is DB2BaseDataSource.NOT_SET (0). If the connection is to a Db2 for z/OS server, caching of dynamic statements for a connection is not done if the property is not set. If the connection is to an IBM Informix data source, caching of dynamic statements for a connection is done if the property is not set.

keepDynamic is used with the DB2Binder -keepdynamic option. The keepDynamic property value that is specified must match the -keepdynamic value that was specified when DB2Binder was run.

For a Db2 for z/OS database server, dynamic statement caching can be done only if the EDM dynamic statement cache is enabled on the data source. The CACHEDYN subsystem parameter must be set to DB2BaseDataSource.YES to enable the dynamic statement cache.

maxTransportObjects
Specifies the maximum number of transport objects that can be used for all connections with the associated DataSource object. The IBM Data Server Driver for JDBC and SQLJ uses transport objects and a global transport objects pool to support the connection concentrator and sysplex workload balancing. There is one transport object for each physical connection to the data source.

The data type of this property is int.

The maxTransportObjects value is ignored if the enableConnectionConcentrator or enableSysplexWLB properties are not set to enable the use of the connection concentrator or sysplex workload balancing.

If the maxTransportObjects value has not been reached, and a transport object is not available in the global transport objects pool, the pool creates a new transport object. If the maxTransportObjects value has been reached, the application waits for the amount of time that is specified by the db2.jcc.maxTransportObjectWaitTime configuration property. After that amount of time has elapsed, if there is still no available transport object in the pool, the pool throws an SQLException.

maxTransportObjects does **not** override the db2.jcc.maxTransportObjects configuration property. maxTransportObjects has no effect on connections from other DataSource objects.
If the maxTransportObjects value is larger than the db2.jcc.maxTransportObjects value, maxTransportObjects does not increase the db2.jcc.maxTransportObjects value.

For version 3.63 or 4.13 or later of the IBM Data Server Driver for JDBC and SQLJ, the default value for maxTransportObjects is 1000. For earlier versions of the IBM Data Server Driver for JDBC and SQLJ, the default value for maxTransportObjects is -1, which means that the number of transport objects for the DataSource is limited only by the db2.jcc.maxTransportObjects value for the driver.

Related concepts
"Example of enabling Db2 for z/OS sysplex workload balancing and automatic client reroute in Java applications" on page 612
Java client setup for sysplex workload balancing and automatic client reroute includes setting several IBM Data Server Driver for JDBC and SQLJ properties.

Common IBM Data Server Driver for JDBC and SQLJ properties for IBM Informix and Db2 on Linux, UNIX, and Windows systems

Some of the IBM Data Server Driver for JDBC and SQLJ properties apply to IBM Informix and Db2 on Linux, UNIX, and Windows systems database servers.

Properties that apply to IBM Informix and Db2 on Linux, UNIX, and Windows systems are:

currentLockTimeout
Specifies whether Db2 on Linux, UNIX, and Windows systems servers wait for a lock when the lock cannot be obtained immediately. The data type of this property is int. Possible values are:

integer
Wait for integer *seconds*. *integer* is between -1 and 32767, inclusive.

LOCK_TIMEOUT_NO_WAIT
Do not wait for a lock. This is the default.

LOCK_TIMEOUT_WAIT_INDEFINITELY
Wait indefinitely for a lock.

LOCK_TIMEOUT_NOT_SET
Use the default for the data source.

memberConnectTimeout
Specifies the amount of time in seconds before an attempt to open a socket to a member of a Db2 for z/OS data sharing group, Db2 pureScale instance, or IBM Informix high availability cluster fails. The data type of this property is int.

memberConnectTimeout applies only to socket connection attempts to different members during automatic client reroute processing. The memberConnectTimeout property takes precedence over the loginTimeout property.

For connections to Db2 for z/OS data servers, the default is 1 second. For connections to other data servers, the default is 0.

If the memberConnectTimeout value is less than or equal to 0, the driver uses the loginTimeout value to determine how long to wait before it fails a connection request.

The memberConnectTimeout value is used for every socket open operation to each member in a member list.

For a connection to a Db2 for z/OS data sharing group, after all attempts to open a socket to all members fail, the driver retries the socket open by using a group IP address. For that retry, the driver uses the loginTimeout value to determine how long to wait before it fails the connection request.

IBM Data Server Driver for JDBC and SQLJ properties for Db2 on Linux, UNIX, and Windows systems

Some of the IBM Data Server Driver for JDBC and SQLJ properties apply only to Db2 on Linux, UNIX, and Windows systems servers.

Those properties are:

accessToken
Identifies the token that is used for authentication at the server. Specifying an access token is valid only if property securityMechanism is set to TOKEN_SECURITY. The data type of this property is String. The maximum length of accessToken is 8000 bytes.

If accessToken is specified, property accessTokenType must also be specified. accessToken cannot be specified when property user or property apiKey is also specified.

This property applies only to SSL connections. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems.

accessTokenType
Identifies the type of access token that is specified in configuration, Connection, or DataSource property accessToken. The token type must be supported by the server. Specifying an access token type is valid only if property securityMechanism is set to TOKEN_SECURITY. The data type of this property is String. The maximum length of accessTokenType is 255 bytes.

This property applies only to SSL connections. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems.

alternateGroupDatabaseName
Specifies the database names for alternate groups to which an application can connect. The data type of this property is String. For a connection to a Db2 for z/OS data server, this value is the location name for a data sharing group. For a connection to a Db2 on Linux, UNIX, and Windows systems data server, each of these values is the database name for a single-member or multiple-member database

instance. If more than one database name is specified, the database names must be separated by commas.

For connections to Db2 for z/OS, only one value can be specified.

alternateGroupPortNumber
Specifies the port numbers for alternate groups to which an application can connect. The data type of this property is String. For a connection to a Db2 for z/OS data server, this value is the TCP/IP server port number that is assigned to the data sharing group. For a connection to a Db2 on Linux, UNIX, and Windows systems data server, each of these values is the TCP/IP server port number that is assigned to a single-member or multiple-member database instance. If more than one port number is specified, the port numbers must be separated by commas.

For connections to Db2 for z/OS, only one value can be specified.

alternateGroupServerName
Specifies the host names for alternate groups to which an application can connect. The data type of this property is String. The data type of this property is String. For a connection to a Db2 for z/OS data server, this value is the domain name or IP address that is assigned to the data sharing group. For a connection to a Db2 on Linux, UNIX, and Windows systems data server, each of these values is the domain name or IP address that is assigned to a a single-member or multiple-member database instance. If more than one host name is specified, the host names must be separated by commas.

For connections to Db2 for z/OS, only one value can be specified.

apiKey
Identifies the API key that is used for authentication at the server. Specifying an API key is valid only if the securityMechanism property is set to PLUGIN_SECURITY. The data type of this property is String. The maximum length of apiKey is 8000 bytes.

apiKey cannot be specified when property user or property accessToken is also specified.

This property applies only to SSL connections. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems.

connectNode
Specifies the target database partition server that an application connects to. The data type of this property is int. The value can be between 0 and 999. The default is database partition server that is defined with port 0. connectNode applies to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems servers only.

currentExplainSnapshot
Specifies the value for the CURRENT EXPLAIN SNAPSHOT special register. The CURRENT EXPLAIN SNAPSHOT special register enables and disables the Explain snapshot facility. The data type of this property is String. The maximum length is eight bytes. This property applies only to connections to data sources that support the CURRENT EXPLAIN SNAPSHOT special register, such as Db2 on Linux, UNIX, and Windows systems.

currentQueryOptimization
Specifies a value that controls the class of query optimization that is performed by the database manager when it binds dynamic SQL statements. The data type of this property is int. The possible values of currentQueryOptimization are:

0
Specifies that a minimal amount of optimization is performed to generate an access plan. This class is most suitable for simple dynamic SQL access to well-indexed tables.

1
Specifies that optimization roughly comparable to Db2 on Linux, UNIX, and Windows systems Version 1 is performed to generate an access plan.

2
Specifies a level of optimization higher than that of Db2 on Linux, UNIX, and Windows systems Version 1, but at significantly less optimization cost than levels 3 and above, especially for very complex queries.

3
Specifies that a moderate amount of optimization is performed to generate an access plan.

5
Specifies a significant amount of optimization is performed to generate an access plan. For complex dynamic SQL queries, heuristic rules are used to limit the amount of time spent selecting an access plan. Where possible, queries will use materialized query tables instead of the underlying base tables.

7
Specifies a significant amount of optimization is performed to generate an access plan. This value is similar to 5 but without the heuristic rules.

9
Specifies the maximum amount of optimization is performed to generate an access plan. This can greatly expand the number of possible access plans that are evaluated. This class should be used to determine if a better access plan can be generated for very complex and very long-running queries using large tables. Explain and performance measurements can be used to verify that a better plan has been generated.

disableClientInputDataConversion
Specifies whether the IBM Data Server Driver for JDBC and SQLJ converts certain types of numeric client data before sending the data to a Db2 on Linux, UNIX, and Windows systems data server.

The affected source and target data types are listed in NUMBER data type. For information on mappings between Java data types and data server data types, see "Data types that map to database data types in Java applications" on page 207.

Disabling conversion might be necessary when the DB2_COMPATIBILITY_VECTOR registry variable on the data server is set to X'10'.

Possible values are:

com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0)
Specifies that the IBM Data Server Driver for JDBC and SQLJ converts the client data to the target data type. 0 is the default.

com.ibm.db2.jcc.DB2BaseDataSource.YES (1)
Specifies that the IBM Data Server Driver for JDBC and SQLJ does not convert the client data to the target data type.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2)
Specifies that the IBM Data Server Driver for JDBC and SQLJ converts the client data to the target data type.

enableAlternateGroupSeamlessACR
Specifies whether failover to an alternate group is seamless or non-seamless. The data type of this property is boolean. The possible values are:

false
Failover is non-seamless. `false` is the default.

With non-seamless behavior, if an application that is currently connected to a primary group is executing a transaction, and the entire primary group goes down, the IBM Data Server Driver for JDBC and SQLJ fails over to alternate group. If failover is successful, the driver throws an `SQLException` with SQL error code -30108.

true
Failover is seamless.

With seamless behavior, if an application that is currently connected to a primary group is executing a transaction, and the entire primary group goes down, the IBM Data Server Driver for JDBC and SQLJ fails over to alternate group. If the transaction is eligible for seamless failover, the connection is retried. If the connection is successful, no `SQLException` is thrown.

For connections to Db2 for z/OS, only one value can be specified.

enableDualTransportUsingDifferentProcess
Specifies the protocol that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use for a dual transport or multi-transport transaction model. The possible values are:

com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0)
Specifies that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use a protocol in which the Java runtime environment does not free Xid objects after an xa_end call. The objects are available until an xa_commit or xa_rollback call is issued. This value is the default.

com.ibm.db2.jcc.DB2BaseDataSource.YES (1)
Specifies that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use a protocol in which the Java runtime environment frees Xid objects after an xa_end call. An application might need to set this value for transaction managers that use the IBM Data Server Driver for JDBC and SQLJ to issue xa_start and xa_end calls, but use some other means to issue xa_prepare, xa_commit, or xa_rollback calls. An example of such a transaction manager is IBM MQ.

The behavior for a property value of com.ibm.db2.jcc.DB2BaseDataSource.YES (1) takes effect only when the xaNetworkOptimization property and the enableSysplexWLB property are set to `false`.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2)
Specifies that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use a protocol in which the Java runtime environment does not free Xid objects after an xa_end call. The objects are available until an xa_commit or xa_rollback call is issued. This value is the default.

includeModLevelInProductVersion
Specifies whether the string that is returned by `DatabaseMetaData.getDatabaseProductVersion` includes the modification and fix pack levels. The data type of this property is int. Possible values are:

com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0)

Specifies that the string that is returned by `DatabaseMetaData.getDatabaseProductVersion` has the format *pppvvrrmf* for Db2 on Linux, UNIX, and Windows systems Version 11.1 modification 1 fix pack 1 or later, and *pppvvrrf* for Db2 on Linux, UNIX, and Windows systems Version 11.1 GA or earlier. This is the default.

com.ibm.db2.jcc.DB2BaseDataSource.YES (1)

Specifies that the string that is returned by `DatabaseMetaData.getDatabaseProductVersion` includes the modification level. The value that is returned is in the format *pppvvrrmf* for Db2 on Linux, UNIX, and Windows systems Version 11.1 modification 1 fix pack 1 or later, and *pppvvrr0f* for Db2 on Linux, UNIX, and Windows systems Version 11.1 fix pack 0 or earlier.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2)

Specifies that the string that is returned by `DatabaseMetaData.getDatabaseProductVersion` does not include the modification level. The value that is returned is in the format *pppvvrrf* for Db2 on Linux, UNIX, and Windows systems Version 11.1 modification 1 fix pack 1 or later, and *pppvvrrf* for Db2 on Linux, UNIX, and Windows systems Version 11.1 fix pack 0 or earlier.

This setting is not recommended if the data server might be Db2 on Linux, UNIX, and Windows systems Version 11.1 modification 1 fix pack 1 or later.

optimizationProfile
Specifies an optimization profile that is used during SQL optimization. The data type of this property is String. The optimizationProfile value is used to set the OPTIMIZATION PROFILE special register. The default is null.

optimizationProfile applies to Db2 on Linux, UNIX, and Windows systems servers only.

optimizationProfileToFlush
Specifies the name of an optimization profile that is to be removed from the optimization profile cache. The data type of this property is String. The default is null.

plugin
The name of a client-side JDBC security plug-in. This property has the `Object` type and contains a new instance of the JDBC security plug-in method.

pluginName
The name of a server-side security plug-in module.

retryWithAlternativeSecurityMechanism
Specifies whether the IBM Data Server Driver for JDBC and SQLJ retries a connection with an alternative security mechanism if the security mechanism that is specified by property securityMechanism is not supported by the data source. The data type of this property is int. The possible values are:

com.ibm.db2.jcc.DB2BaseDataSource.YES (1)
Retry the connection using an alternative security mechanism. The IBM Data Server Driver for JDBC and SQLJ issues warning code +4222 and retries the connection with the most secure available security mechanism.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2) or com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0)
Do not retry the connection using an alternative security mechanism.

retryWithAlternativeSecurityMechanism applies to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity connections to Db2 on Linux, UNIX, and Windows systems only.

useTransactionRedirect
Specifies whether the Db2 system directs SQL statements to different database partitions for better performance. The data type of this property is boolean. The default is `false`.

This property is applicable only under the following conditions:

- The connection is to a Db2 on Linux, UNIX, and Windows systems server that uses a partitioned database environment.
- The partitioning key remains constant throughout a transaction.

If useTransactionRedirect is `true`, the IBM Data Server Driver for JDBC and SQLJ sends connection requests to the DPF node that contains the target data of the first directable statement in the transaction. Db2 on Linux, UNIX, and Windows systems then directs the SQL statement to different partitions as needed.

IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS

Some of the IBM Data Server Driver for JDBC and SQLJ properties apply only to Db2 for z/OS servers.

The following list includes the properties for the IBM Data Server Driver for JDBC and SQLJ:

accountingInterval
Specifies whether Db2 accounting records are produced at commit points or on termination of the physical connection to the data source. The data type of this property is String.

If the value of `accountingInterval` is "COMMIT", and there are no open, held cursors, Db2 writes an accounting record each time that the application commits work. If the value of `accountingInterval` is "COMMIT", and the application performs a commit operation while a held cursor is open, the accounting interval spans that commit point. The accounting interval also ends at the next valid accounting interval end point. If the value of `accountingInterval` is not "COMMIT", accounting records are produced on termination of the physical connection to the data source.

The `accountingInterval` property sets the *accounting-interval* parameter for an underlying RRSAF sign-on call. If the value of subsystem parameter ACCUMACC is not NO, the ACCUMACC value overrides the `accountingInterval` setting.

The `accountingInterval` property applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. The `accountingInterval` property is not applicable to connections under CICS or IMS, or for Java stored procedures.

The `accountingInterval` property overrides the db2.jcc.accountingInterval configuration property.

charOutputSize
Specifies the maximum number of bytes to use for INOUT or OUT stored procedure parameters that are registered as `Types.CHAR` `charOutputSize` applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS database servers.

Because DESCRIBE information for stored procedure INOUT and OUT parameters is not available at run time, by default, the IBM Data Server Driver for JDBC and SQLJ sets the maximum length of each character INOUT or OUT parameter to 32767. For stored procedures with many `Types.CHAR` parameters, this maximum setting can result in allocation of much more storage than is necessary.

To use storage more efficiently, set `charOutputSize` to the largest expected length for any `Types.CHAR` INOUT or OUT parameter.

The `charOutputSize` property has no effect on INOUT or OUT parameters that are registered as `Types.VARCHAR` or `Types.LONGVARCHAR`. The driver uses the default length of 32767 for `Types.VARCHAR` and `Types.LONGVARCHAR` parameters.

Before you choose the value for `charOutputSize`, you need to consider the possibility of expansion during character conversion. Because the IBM Data Server Driver for JDBC and SQLJ has no information about the server-side CCSID that is used for output parameter values, the driver requests the stored procedure output data in UTF-8 Unicode. The `charOutputSize` value needs to be the maximum number of bytes that are needed after the parameter value is converted to UTF-8 Unicode. UTF-8 Unicode characters can require up to 3 bytes. (The euro symbol is an example of a 3-byte UTF-8 character). To ensure that the value of `charOutputSize` is large enough, if you have no information about the output data, set `charOutputSize` to three times the defined length of the largest CHAR parameter.

clientApplcompat
For connections to Db2 12 for z/OS data servers at a function level of V12R1M501 or later, sets the capabilities of a particular instance of the IBM Data Server Driver for JDBC and SQLJ to a function level that is less than or equal to the function level of the data server.

For example, suppose that the driver packages for an instance of the IBM Data Server Driver for JDBC and SQLJ are bound with an APPLCOMPAT value of V12R1M501. Some applications that use that instance of the driver need only the capabilities in function level V12R1M500. You can set `clientApplcompat` to V12R1M500 for those applications to use only capabilities of the V12R1M500 function level.

If the driver packages have an APPLCOMPAT value of V12R1M500 or less, and `clientApplcompat` is not set, the APPLCOMPAT setting determines the set of capabilities that the client application can use.

If the driver packages have an APPLCOMPAT value of V12R1M501 or greater, setting `clientApplcompat` is optional. However, if `clientApplcompat` is not set, the data server rejects a connection if the IBM Data Server Driver for JDBC and SQLJ is at a level that does not support the APPLCOMPAT bind option value of the Db2 12 for z/OS package.

For more information, see V12R1Mnnn application compatibility levels for data server clients and drivers (Db2 Application programming and SQL).

clientUser
Specifies the current client user name for the connection. This information is for client accounting purposes. Unlike the JDBC connection user name, this value can change during a connection. For a Db2 for z/OS server, the maximum length is 16 bytes.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

clientWorkstation
Specifies the workstation name for the current client for the connection. This information is for client accounting purposes. This value can change during a connection. The data type of this property is String. For a Db2 for z/OS server, the maximum length is 18 bytes. A Java empty string ("") is valid for this value, but a Java `null` value is not valid.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

currentLocaleLcCtype
Specifies the LC_CTYPE locale that is used to execute SQL statements that use a built-in function that references a locale. The data type of this property is String. If `currentLocaleLcCtype` is set, the IBM Data Server Driver for JDBC and SQLJ sets the CURRENT LOCALE LC_CTYPE special register on the data server to the property value. The `currentLocaleLcCtype` property has no default.

The `currentLocaleLcCtype` property can be set only at the start of a connection, and cannot be changed while the connection is active.

currentSQLID
The `currentSQLID` property specifies the following information:

- The authorization ID that is used for authorization checking on dynamically prepared CREATE, GRANT, and REVOKE SQL statements.
- The owner of a table space, database, storage group, or synonym that is created by a dynamically issued CREATE statement.
- The implicit qualifier of all table, view, alias, and index names specified in dynamic SQL statements.

The `currentSQLID` property sets the value in the CURRENT SQLID special register on a Db2 for z/OS server. If the `currentSQLID` property is not set, the default schema name is the value in the CURRENT SQLID special register.

enableMultiRowInsertSupport
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses multi-row INSERT for batched INSERT or MERGE operations, when the target data server is a Db2 for z/OS server that supports multi-row INSERT. The batch operations must be `PreparedStatement` calls with parameter markers. The data type of this property is Boolean. The default is `true`.

The `enableMultiRowInsertSupport` value cannot be changed during a connection. The `enableMultiRowInsertSupport` property must be set to `false` if INSERT FROM SELECT statements are executed in a batch. Otherwise, the driver produces a `BatchUpdateException` error.

enableSeamlessFailoverErrorCodes
Specifies whether the IBM Data Server Driver for JDBC and SQLJ maps seamless error codes, such as -4498, -30108, or -20542, to communication error code -4499. The data type of this property is Boolean. Possible values are:

true
The IBM Data Server Driver for JDBC and SQLJ does not map seamless errors to communication error code -4499. The application receives different error codes, depending on the types of errors that occurred.

false
The IBM Data Server Driver for JDBC and SQLJ maps seamless errors to communication error code -4499. If a seamless error occurs during execution of an application, the driver throws an exception with error code -4499. `false` is the default.

enableSeamlessFailoverErrorCodes applies to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS only.

enableT2zosLBF
Specifies whether limited block fetch is used for connections that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to retrieve data from a table on a local Db2 for z/OS data server. The data type of this property is an int. You must use one of the following possible values of the property:

com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0) or not specified
This value is the default setting.

- For a connection to a Db2 for z/OS data server in Version 10 conversion mode, specifies that limited block fetch is not used for retrieving data from a local table that uses the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.
- For a connection to a Db2 for z/OS data server in Version 10 new-function mode or later, specifies that limited block fetch is used for retrieving data from a local table that uses the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

com.ibm.db2.jcc.DB2BaseDataSource.YES (1)
Specifies that limited block fetch is used for retrieving data from a local table that uses the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

If you set this property to 1, and IBM Db2 Analytics Accelerator for z/OS might also need to be switched on during cursor reuse, you need to set configuration property db2.jcc.enableT2zosLBFSwitchWithIDAA to 1.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2)
Specifies that limited block fetch is not used for retrieving data from a local table that uses the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

The `enableT2zosLBF` property applies to Db2 for z/OS data servers in Version 10 new-function mode or later. The `enableT2zosLBF` property does not apply to retrieval of stored procedure result sets.

enableT2zosLBFSPResultSets
Specifies whether limited block fetch is used for connections that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to retrieve data from a stored procedure result set on a local Db2 for z/OS data server. The data type of this property is int. The following are possible values of the property:

com.ibm.db2.jcc.DB2BaseDataSource.YES (1) or
com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0)
Specifies that limited block fetch is used for retrieving data from a stored procedure result set that uses the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity. This value is the default.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2)
Specifies that limited block fetch is not used for retrieving data from a stored procedure result set that uses the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

The `enableT2zosLBFSPResultSets` property applies to Db2 for z/OS data servers in Version 10 new-function mode or later.

enableXACleanTransaction
Specifies whether to reset session data at XA End. The data type of `enableXACleanTransaction` is Boolean. Possible values of the property include the following Boolean values:

true
Enables clean transaction mode. All database resources such as cursors and DGTTs, are implicitly closed and dropped on XA_END.

false
Enable dirty transaction mode. This value is the default. Session data is not reset at XA End, and persists across transactions.

extendedTableInfo
The `extendedTableInfo` property specifies whether information about extended table types is returned from a `DatabaseMetaData.getTables` method call. Currently, there exists one extended table type: ACCEL-ONLY TABLE.

com.ibm.db2.jcc.DB2BaseDataSource.NO (2) or
com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET (0)
The result set that is returned by the `DatabaseMetaData.getTables` method does not contain columns for extended table types.

Rows for extended table types are returned only if "TABLE" is explicitly specified in the *types* parameter value. In this case, extended table types are listed as TABLE in the TABLE_TYPE column of the result set.

com.ibm.db2.jcc.DB2BaseDataSource.YES (1)
The result set that is returned by the `DatabaseMetaData.getTables` method contains rows and columns for extended table types. The following list depicts the result set in more detail:

- The result set contains these extra columns after the columns that are always returned in the result set from `DatabaseMetaData.getTables`:

Table 40. Extra columns returned by `DatabaseMetaData.getTables`

Column Name	Data type	Description
TEMPORAL_TABLE_TYPE	String	Contains the type of temporal table. The following shows possible values of the temporal table: **SYSTEM** System-period temporal table. **APPLICATION** Application-period temporal table. **BITEMPORAL** Bitemporal table. **Empty string** Not a temporal table. This row is returned for connections to Db2 for z/OS Version 10 or later.
IS_ACCELERATED	String	Indicates whether the table is an accelerated table. Possible values are YES or NO. This row is returned for connections to Db2 for z/OS Version 10 or later.
ACCEL_ARCHIVE_STATUS	String	Contains the archive status of the table in the accelerator database. See the description of the ARCHIVE column in SYSACCEL.SYSACCELERATEDTABLES table (Db2 SQL) for the possible values and their meanings. This row is returned for connections to Db2 for z/OS Version 10 or later.
IS_ARCHIVE_ENABLED	String	Indicates whether the table is an archive-enabled table. Possible values are YES or NO. This row is returned for connections to Db2 for z/OS Version 11 or later.

- Rows for extended table types are returned under the following circumstances:
  - All table types are implicitly requested by specifying null in the *types* parameter value.
  - An extended table type name is explicitly specified in the *types* parameter value.

    In this case, the extended table type is listed by its extended table type name in the TABLE_TYPE column of the result set.

jdbcCollection
Specifies the collection ID for the packages that are used by an instance of the IBM Data Server Driver for JDBC and SQLJ at run time. The data type of `jdbcCollection` is String. The default is NULLID.

This property is used with the DB2Binder **-collection** option. The DB2Binder utility must contain bounded IBM Data Server Driver for JDBC and SQLJ packages at the server by using a **-collection** value that matches the `jdbcCollection` value.

The `jdbcCollection` setting does not determine the collection that is used for SQLJ applications. For SQLJ, the collection is determined by the **-collection** option of the SQLJ customizer.

The `jdbcCollection` setting does not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

keyUsage

The `keyUsage` property is used only for client certificate selection of `keyUsage`-based certificates from the WINDOWS-MY keystore type. The PKI Card supports the WINDOWS-MY keystore type and WINDOWS-ROOT truststore type. It does not apply on the server certificate for server certificate authentication. If dataSource or Connection is configured with the securityMechanism, TLS_CLIENT_CERTIFICATE_SECURITY, then `keyUsage` is applied on the Connection object to select the client certificate.

If dataSource or Connection is not configured with the securityMechanism, `TLS_CLIENT_CERTIFICATE_SECURITY`, the JCC driver ignores the `keyUsage` property and proceeds with the default settings for an SSL connection. For possible values of the `keyUsage` property, see the following table.

Table 41. keyUsage constants

Certificate keyUsage constant	Values
`com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET`	0
`com.ibm.db2.jcc.DB2BaseDataSource.digitalSignature`	1
`com.ibm.db2.jcc.DB2BaseDataSource.nonRepudiation`	2
`com.ibm.db2.jcc.DB2BaseDataSource.keyEncipherment`	4
`com.ibm.db2.jcc.DB2BaseDataSource.dataEncipherment`	8
`com.ibm.db2.jcc.DB2BaseDataSource.keyAgreement`	16
`com.ibm.db2.jcc.DB2BaseDataSource.keyCertSign`	32
`com.ibm.db2.jcc.DB2BaseDataSource.cRLSign`	64
`com.ibm.db2.jcc.DB2BaseDataSource.encipherOnly`	128
`com.ibm.db2.jcc.DB2BaseDataSource.decipherOnly`	256

The default value of this integer property is 0 (NOT SET). The `keyUsage` constants (other than `KeyUsage_ALL`, -1) are numerically additive. To specify multiple `keyUsage` components (as specified by their corresponding `keyUsage` constants) in the `keyUsage` property, combine the preferred `keyUsage` constants by using numeric addition. For example, suppose that this trace specification is needed:

```
(digitalSignature |
 nonRepudiation |
 keyEncipherment |
 dataEncipherment |
 keyAgreement |
 cRLSign)
```

You need to set keyUsage to the sum of the integer values of these constants:

```
1 + 2 + 4 + 16 + 32 + 64 = 119
```

. Therefore, keyUsage must be set to 119 to enable these keyUsage components.

maxConnCachedParamBufferSize
Specifies the maximum size of an internal buffer that is used for caching input parameter values for PreparedStatement objects. The buffer caches values on the native code side that are passed from the driver's Java code side for the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. The buffer is used by all PreparedStatement objects for a Connection. The default is 1048576 (1 MB). The default value must be adequate for most users. Set maxConnCachedParamBufferSize to a larger value if many applications that run under the driver instance have PreparedStatement objects with large numbers of input parameters or large input parameters. The maxConnCachedParamBufferSize value must be larger than the maximum size of all input parameter data for a Connection. However, you also need to consider the total number of connections and the maximum amount of memory that is available when you set the maxConnCachedParamBufferSize value.

The buffer exists for the life of a Connection, unless it reaches the maximum size. If that happens, the buffer is freed on each call to the native code. The corresponding buffer on the Java code side is freed on PreparedStatement.clearParameters and PreparedStatement.close calls. The buffers are not cleared if an application calls PreparedStatement.clearParameters, and the buffers do not reach the maximum size.

maxRowsetSize
Specifies the maximum number of bytes that are used for rowset buffering for each statement, when the IBM Data Server Driver for JDBC and SQLJ uses multiple-row FETCH for cursors. The data type of this property is int. The default is 32767.

The maxRowsetSize property applies only to the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

pkList
Specifies a package list that is used for the underlying RRSAF CREATE THREAD call when a JDBC or SQLJ connection to a data source is established. The pkList property applies only to the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Specify this property if you do not bind plans for your SQLJ programs or for the JDBC driver. If you specify this property, **do not specify planName.**

Recommendation: Use pkList instead of planName.

The following is the format of the package list:

The pkList property overrides the value of the db2.jcc.pkList configuration property. If pkList, planName, and db2.jcc.pkList are not specified, then the value of pkList is NULLID.*.

planName
Specifies a Db2 plan name that is used for the underlying RRSAF CREATE THREAD call when a JDBC or SQLJ connection to a data source is established. planName applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Specify this property if you bind plans for your SQLJ programs and for the JDBC driver packages. If you specify this property, **do not specify pkList.**

The planName property overrides the value of the db2.jcc.planName configuration property. If pkList, planName, and db2.jcc.planName are not specified, NULLID.* is used as the package list for the underlying CREATE THREAD call.

queryAcceleration
Specifies the value that is to be used for the CURRENT QUERY ACCELERATION special register. The data type of this property is String. Possible values are:

NONE

Specifies that no query acceleration is done.

ENABLE
Specifies that queries are accelerated only if Db2 for z/OS determines that it is advantageous to do so. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 for z/OS returns an SQL error to the application.

ENABLE WITH FAILBACK
Specifies that queries are accelerated only if Db2 for z/OS determines that it is advantageous to do so. If the accelerator returns an error during the PREPARE or first OPEN for the query, Db2 for z/OS executes the query without the accelerator. If the accelerator returns an error during a FETCH or a subsequent OPEN, Db2 for z/OS returns the error to the user, and does not execute the query.

ELIGIBLE
Specifies that queries are accelerated if they are eligible for acceleration. Db2 for z/OS does not use cost information to determine whether to accelerate the queries. Queries that are not eligible for acceleration are executed by Db2 for z/OS. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 for z/OS returns an SQL error to the application.

ALL
Specifies that queries are accelerated if they are eligible for acceleration. Db2 for z/OS does not use cost information to determine whether to accelerate the queries. Queries that are not eligible for acceleration are not executed by Db2 for z/OS, and an SQL error is returned. If there is an accelerator failure while a query is running, or the accelerator returns an error, Db2 for z/OS returns an SQL error to the application.

reportLongTypes
Specifies whether `DatabaseMetaData` methods report LONG VARCHAR and LONG VARGRAPHIC column data types as long data types. The data type of this property is short. Possible values are:

`com.ibm.db2.jcc.DB2BaseDataSource.NO` (2) or `com.ibm.db2.jcc.DB2BaseDataSource.NOT_SET` (0)
Specifies that `DatabaseMetaData` methods that return information about a LONG VARCHAR or LONG VARGRAPHIC column return `java.sql.Types.VARCHAR` in the DATA_TYPE column and VARCHAR or VARGRAPHIC in the TYPE_NAME column of the result set. This value is the default for Db2 for z/OS Version 9 or later.

`com.ibm.db2.jcc.DB2BaseDataSource.YES` (1)
Specifies that `DatabaseMetaData` methods that return information about a LONG VARCHAR or LONG VARGRAPHIC column return `java.sql.Types.LONGVARCHAR` in the DATA_TYPE column of the result set. The method also returns a LONG VARCHAR or LONG VARGRAPHIC in the TYPE_NAME column of the result set.

sendCharInputsUTF8
Specifies whether the IBM Data Server Driver for JDBC and SQLJ converts character input data to the CCSID of the Db2 for z/OS database server, or sends the data in UTF-8 encoding for conversion by the database server. sendCharInputsUTF8 applies to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS database servers only. The data type of this property is int. If this property is also set at the driver level (db2.jcc.sendCharInputsUTF8), this value overrides the driver-level value.

The following shows possible values of the property:

`com.ibm.db2.jcc.DB2BaseDataSource.NO` (2)
Specifies that the IBM Data Server Driver for JDBC and SQLJ converts character input data to the target encoding before the data is sent to the Db2 for z/OS database server. com.ibm.db2.jcc.DB2BaseDataSource.NO is the default.

`com.ibm.db2.jcc.DB2BaseDataSource.YES (1)`
Specifies that the IBM Data Server Driver for JDBC and SQLJ sends character input data to the Db2 for z/OS database server in UTF-8 encoding. The database server converts the data from UTF-8 encoding to the target CCSID.

Specify com.ibm.db2.jcc.DB2BaseDataSource.YES only if conversion to the target CCSID by the SDK for Java causes character conversion problems. The most common problem occurs when you use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to insert a Unicode line feed character (U+000A) into a table column that has CCSID 37, and then retrieve that data from a non-z/OS client. If the SDK for Java does the conversion during insertion of the character into the column, the line feed character is converted to the EBCDIC new line character X'15'. However, during retrieval, some SDKs for Java on operating systems other than z/OS convert the X'15' character to the Unicode next line character (U+0085) instead of the line feed character (U+000A). The next line character causes unexpected behavior for some XML parsers. If you set sendCharInputsUTF8 to com.ibm.db2.jcc.DB2BaseDataSource.YES, the Db2 for z/OS database server converts the U+000A character to the EBCDIC line feed character X'25' during insertion into the column. Therefore, the character is always retrieved as a line feed character.

Conversion of data to the target CCSID on the database server might cause the IBM Data Server Driver for JDBC and SQLJ to use more memory than conversion by the driver. The driver allocates memory for conversion of character data from the source encoding to the encoding of the data that it sends to the database server. The amount of space that the driver allocates for character data that is sent to a table column is based on the maximum length of the data. UTF-8 data can require up to 3 bytes for each character. Therefore, if the driver sends UTF-8 data to the database server, the driver needs to allocate three times the maximum number of characters in the input data. If the driver does the conversion, and the target CCSID is a single-byte CCSID, the driver needs to allocate only the maximum number of characters in the input data.

sessionTimeZone
Specifies the setting for the CURRENT SESSION TIME ZONE special register. The data type of this property is String.

The `sessionTimeZone` value is a time zone value that is in the format of *sth:tm*. The *s* in the format is the sign, *th* is the time zone hour, and *tm* is time zone minutes. The range of valid values is -12:59 to +14:00.

sqljEnableClassLoaderSpecificProfiles
Specifies whether the IBM Data Server Driver for JDBC and SQLJ allows the use and loading of SQLJ profiles with the same Java name in multiple J2EE application (.ear) files. The data type of this property is Boolean. The default is `false`. The `sqljEnableClassLoaderSpecificProfiles` property is a dataSource property. This property is primarily intended for use with WebSphere Application Server.

ssid
Specifies the name of the local Db2 for z/OS subsystem to which a connection is established by using the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. The data type of this property is String.

The `ssid` property overrides the db2.jcc.ssid configuration property.

The `ssid` property can be the subsystem name for a local subsystem or a group attachment name or subgroup attachment name.

Specification of a single local subsystem name allows more than one subsystem on a single LPAR to be accessed as a local subsystem for connections that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

Specification of a group attachment name or subgroup attachment name allows failover processing to occur if a data sharing group member fails. If the Db2 subsystem to which an application is connected fails, the connection ends. However, when new connections use that group attachment name or subgroup attachment name, Db2 for z/OS uses group or subgroup attachment processing to find an active Db2 subsystem to which to connect.

The ssid property applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS.

sslKeyStoreLocation
Specifies the full path name of the Java KeyStore on the client that contains the client certificate for an SSL connection. The client certificate is used to identify the client only during mutual authentication or client certificate security.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the sslConnection property is set to true and securityMechanism is set to 18(TLS_CLIENT_CERTIFICATE_SECURITY).

If sslKeyStoreLocation is set, and sslConnection is set to true, the IBM Data Server Driver for JDBC and SQLJ uses the sslKeyStoreLocation value instead of the value in the javax.net.ssl.keyStore Java property.

The default value for sslKeyStoreLocation is provided by the db2.jcc.sslKeyStoreLocation configuration property. If the db2.jcc.sslKeyStoreLocation configuration property is also not specified, then the default value for sslKeyStoreLocation is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

sslKeyStorePassword
Specifies the password for the Java KeyStore on the client that contains the client certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the sslConnection property is set to true and securityMechanism is set to 18(TLS_CLIENT_CERTIFICATE_SECURITY).

If sslKeyStorePassword is set, and sslConnection is set to true, the IBM Data Server Driver for JDBC and SQLJ uses the sslKeyStorePassword value instead of the value in the javax.net.ssl.keyStorePassword Java property.

The default value for sslKeyStorePassword is provided by the db2.jcc.sslKeyStorePassword configuration property. If the db2.jcc.sslKeyStorePassword configuration property is also not specified, then the default value for sslKeyStorePassword is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

sslKeyStoreType
Specifies the type of the Java KeyStore on the client that contains the client certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the sslConnection property is set to true and securityMechanism is set to 18(TLS_CLIENT_CERTIFICATE_SECURITY).

If sslKeyStoreType is set, and sslConnection is set to true, the IBM Data Server Driver for JDBC and SQLJ uses the sslKeyStoreType value instead of the value in the javax.net.ssl.keyStoreType Java property.

The default value for sslKeyStoreType is provided by the db2.jcc.sslKeyStoreType configuration property. If the db2.jcc.sslKeyStoreTypeconfiguration property is also not specified, then the default value for sslKeyStoreType is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

useRowsetCursor
Specifies whether the IBM Data Server Driver for JDBC and SQLJ always uses multiple-row FETCH for scrollable cursors if the data source supports multiple-row FETCH. The data type of this property is Boolean.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, or to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS. If the enableRowsetSupport property is not set, the default for useRowsetCursor is true. If the enableRowsetSupport property is set, the useRowsetCursor property is not used.

Applications that use the JDBC 1 technique for performing positioned update or delete operations must set `useRowSetCursor` to `false`. Those applications do not operate properly if the IBM Data Server Driver for JDBC and SQLJ uses multiple-row FETCH.

Related reference

DDF/RRSAF ACCUM field (ACCUMACC subsystem parameter) (Db2 Installation and Migration)

IBM Data Server Driver for JDBC and SQLJ properties for IBM Informix

Some of the IBM Data Server Driver for JDBC and SQLJ properties apply only to IBM Informix databases. Those properties correspond to IBM Informix environment variables.

Properties that are shown in uppercase characters in the following information must be specified in uppercase. For those properties, `getXXX` and `setXXX` methods are formed by prepending the uppercase property name with `get` or `set`. For example:

```
boolean dbDate = DB2BaseDataSource.getDBDATE();
```

The IBM Informix-specific properties are:

DBANSIWARN

Specifies whether the IBM Data Server Driver for JDBC and SQLJ instructs the IBM Informix database to return an `SQLWarning` to the application if an SQL statement does not use ANSI-standard syntax. The data type of this property is boolean. Possible values are:

false or 0

Do not send a value to the IBM Informix database that instructs the database to return an `SQLWarning` to the application if an SQL statement does not use ANSI-standard syntax. This is the default.

true or 1

Send a value to the IBM Informix database that instructs the database to return an `SQLWarning` to the application if an SQL statement does not use ANSI-standard syntax.

You can use the DBANSIWARN IBM Data Server Driver for JDBC and SQLJ property to set the DBANSIWARN IBM Informix property, but you cannot use the DBANSIWARN IBM Data Server Driver for JDBC and SQLJ property to reset the DBANSIWARN IBM Informix property.

DBDATE

Specifies the end-user format of DATE values. The data type of this property is String. Possible values are in the description of the DBDATE environment variable in *IBM Informix Guide to SQL: Reference*.

The default value is "Y4MD-".

DBPATH

Specifies a colon-separated list of values that identify the database servers that contain databases. The date type of this property is String. Each value can be:

- A full path name
- A relative path name
- The server name of an IBM Informix database server
- A server name and full path name

The default ".".

DBSPACETEMP

Specifies a comma-separated or colon-separated list of existing dbspaces in which temporary tables are placed. The data type of this property is String.

If this property is not set, no value is sent to the server. The value for the DBSPACETEMP environment variable is used.

DBTEMP
Specifies the full path name of an existing directory in which temporary files and temporary tables are placed. The data type of this property is String. The default is "/tmp".

DBUPSPACE
Specifies the maximum amount of system disk space and maximum amount of memory, in kilobytes, that the UPDATE STATISTICS statement can use when it constructs multiple column distributions simultaneously. The data type of this property is String.

The format of DBUPSPACE is "*maximum-disk-space*:*maximum-memory*".

If this property is not set, no value is sent to the server. The value for the DBUPSPACE environment variable is used.

DB_LOCALE
Specifies the database locale, which the database server uses to process locale-sensitive data. The data type of this property is String. Valid values are the same as valid values for the DB_LOCALE environment variable. The default value is null.

DELIMIDENT
Specifies whether delimited SQL identifiers can be used in an application. The data type of this property is boolean. Possible values are:

false
The application cannot contain delimited SQL identifiers. Double quotation marks (") or single quotation marks (') delimit literal strings. This is the default.

true
The application can contain delimited SQL identifiers. Delimited SQL identifiers must be enclosed in double quotation marks ("). Single quotation marks (') delimit literal strings.

IFX_DIRECTIVES
Specifies whether the optimizer allows query optimization directives from within a query. The data type of this property is String. Possible values are:

"1" or "ON"
Optimization directives are accepted.

"0" or "OFF"
Optimization directives are not accepted.

If this property is not set, no value is sent to the server. The value for the IFX_DIRECTIVES environment variable is used.

IFX_EXTDIRECTIVES
Specifies whether the optimizer allows external query optimization directives from the sysdirectives system catalog table to be applied to queries in existing applications. Possible values are:

"1" or "ON"
External query optimization directives are accepted.

"0" or "OFF"
External query optimization are not accepted.

If this property is not set, no value is sent to the server. The value for the IFX_EXTDIRECTIVES environment variable is used.

IFX_UPDDESC
Specifies whether a DESCRIBE of an UPDATE statement is permitted. The data type of this property is String.

Any non-null value indicates that a DESCRIBE of an UPDATE statement is permitted. The default is "1".

IFX_XASTDCOMPLIANCE_XAEND
Specifies whether global transactions are freed only after an explicit rollback, or after any rollback. The data type of this property is String. Possible values are:

"0"
Global transactions are freed only after an explicit rollback. This behavior conforms to the X/Open XA standard.

"1"
Global transactions are freed after any rollback.

If this property is not set, no value is sent to the server. The value for the IFX_XASTDCOMPLIANCE_XAEND environment variable is used.

INFORMIXOPCACHE
Specifies the size of the memory cache, in kilobytes, for the staging-area blobspace of the client application. The data type of this property is String. A value of "0" indicates that the cache is not used.

If this property is not set, no value is sent to the server. The value for the INFORMIXOPCACHE environment variable is used.

INFORMIXSTACKSIZE
Specifies the stack size, in kilobytes, that the database server uses for the primary thread of a client session. The data type of this property is String.

If this property is not set, no value is sent to the server. The value for the INFORMIXSTACKSIZE environment variable is used.

NODEFDAC
Specifies whether the database server prevents default table privileges (SELECT, INSERT, UPDATE, and DELETE) from being granted to PUBLIC when a new table is created during the current session, in a database that is not ANSI compliant. The data type of this property is String. Possible values are:

"yes"
The database server prevents default table privileges from being granted to PUBLIC when a new table is created during the current session, in a database that is not ANSI compliant.

"no"
The database server does not prevent default table privileges from being granted to PUBLIC when a new table is created during the current session, in a database that is not ANSI compliant. This is the default.

OPTCOMPIND
Specifies the preferred method for performing a join operation on an ordered pair of tables. The data type of this property is String. Possible values are:

"0"
The optimizer chooses a nested-loop join, where possible, over a sort-merge join or a hash join.

"1"
When the isolation level is repeatable read, the optimizer chooses a nested-loop join, where possible, over a sort-merge join or a hash join. When the isolation level is not repeatable read, the optimizer chooses a join method based on costs.

"2"
The optimizer chooses a join method based on costs, regardless of the transaction isolation mode.

If this property is not set, no value is sent to the server. The value for the OPTCOMPIND environment variable is used.

OPTOFC
Specifies whether to enable optimize-OPEN-FETCH-CLOSE functionality. The data type of this property is String. Possible values are:

"0"
Disable optimize-OPEN-FETCH-CLOSE functionality for all threads of applications.

"1"
Enable optimize-OPEN-FETCH-CLOSE functionality for all cursors in all threads of applications.

If this property is not set, no value is sent to the server. The value for the OPTOFCD environment variable is used.

PDQPRIORITY
Specifies the degree of parallelism that the database server uses. The PDQPRIORITY value affects how the database server allocates resources, including memory, processors, and disk reads. The data type of this property is String. Possible values are:

"HIGH"
When the database server allocates resources among all users, it gives as many resources as possible to queries.

"LOW" or "1"
The database server fetches values from fragmented tables in parallel.

"OFF" or "0"
Parallel processing is disabled.

If this property is not set, no value is sent to the server. The value for the PDQPRIORITY environment variable is used.

PSORT_DBTEMP
Specifies the full path name of a directory in which the database server writes temporary files that are used for a sort operation. The data type of this property is String.

If this property is not set, no value is sent to the server. The value for the PSORT_DBTEMP environment variable is used.

PSORT_NPROCS
Specifies the maximum number of threads that the database server can use to sort a query. The data type of this property is String. The maximum value of PSORT_NPROCS is "10".

If this property is not set, no value is sent to the server. The value for the PSORT_NPROCS environment variable is used.

STMT_CACHE
Specifies whether the shared-statement cache is enabled. The data type of this property is String. Possible values are:

"0"
The shared-statement cache is disabled.

"1"
A 512 KB shared-statement cache is enabled.

If this property is not set, no value is sent to the server. The value for the STMT_CACHE environment variable is used.

dumpPool
Specifies the types of statistics on global transport pool events that are written, in addition to summary statistics. The global transport pool is used for the connection concentrator and sysplex workload balancing.

The data type of dumpPool is int. dumpPoolStatisticsOnSchedule and dumpPoolStatisticsOnScheduleFile must also be set for writing statistics before any statistics are written.

You can specify one or more of the following types of statistics with the db2.jcc.dumpPool property:

- `DUMP_REMOVE_OBJECT` (hexadecimal: X'01', decimal: 1)
- `DUMP_GET_OBJECT` (hexadecimal: X'02', decimal: 2)
- `DUMP_WAIT_OBJECT` (hexadecimal: X'04', decimal: 4)
- `DUMP_SET_AVAILABLE_OBJECT` (hexadecimal: X'08', decimal: 8)
- `DUMP_CREATE_OBJECT` (hexadecimal: X'10', decimal: 16)
- `DUMP_SYSPLEX_MSG` (hexadecimal: X'20', decimal: 32)
- `DUMP_POOL_ERROR` (hexadecimal: X'80', decimal: 128)

To trace more than one type of event, add the values for the types of events that you want to trace. For example, suppose that you want to trace DUMP_GET_OBJECT and DUMP_CREATE_OBJECT events. The numeric equivalents of these values are 2 and 16, so you specify 18 for the dumpPool value.

The default is 0, which means that only summary statistics for the global transport pool are written.

This property does not have a `setXXX` or a `getXXX` method.

dumpPoolStatisticsOnSchedule
Specifies how often, in seconds, global transport pool statistics are written to the file that is specified by dumpPoolStatisticsOnScheduleFile. The global transport object pool is used for the connection concentrator and sysplex workload balancing.

The default is -1. -1 means that global transport pool statistics are not written.

This property does not have a `setXXX` or a `getXXX` method.

dumpPoolStatisticsOnScheduleFile
Specifies the name of the file to which global transport pool statistics are written. The global transport pool is used for the connection concentrator and sysplex workload balancing.

If dumpPoolStatisticsOnScheduleFile is not specified, global transport pool statistics are not written.

This property does not have a `setXXX` or a `getXXX` method.

maxTransportObjectIdleTime
Specifies the amount of time in seconds that an unused transport object stays in a global transport object pool before it can be deleted from the pool. Transport objects are used for the connection concentrator and sysplex workload balancing.

The default value for maxTransportObjectIdleTime is 10. Setting maxTransportObjectIdleTime to a value less than 0 causes unused transport objects to be deleted from the pool immediately. Doing this is **not** recommended because it can cause severe performance degradation.

This property does not have a `setXXX` or a `getXXX` method.

minTransportObjects
Specifies the lower limit for the number of transport objects in a global transport object pool for the connection concentrator and sysplex workload balancing. When a JVM is created, there are no transport objects in the pool. Transport objects are added to the pool as they are needed. After the minTransportObjects value is reached, the number of transport objects in the global transport object pool never goes below the minTransportObjects value for the lifetime of that JVM.

The default value for minTransportObjects is 0. Any value that is less than or equal to 0 means that the global transport object pool can become empty.

This property does not have a `setXXX` or a `getXXX` method.

IBM Data Server Driver for JDBC and SQLJ configuration properties

The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

The following table summarizes the configuration properties and corresponding `Connection` or `DataSource` properties, if they exist.

Table 42. Summary of Configuration properties and corresponding Connection and DataSource properties

Configuration property name	Connection or DataSource property name	Introduced in driver version	Notes
db2.jcc.accessToken	accessToken	4.24	“6” on page 294
db2.jcc.accessTokenType	accessTokenType	4.27	“6” on page 294
db2.jcc.accountingInterval	accountingInterval	3.6	“1” on page 294, “4” on page 294
db2.jcc.allowSqljDuplicateStaticQueries		2.11	“4” on page 294

Table 42. Summary of Configuration properties and corresponding Connection and DataSource properties (continued)

Configuration property name	Connection or DataSource property name	Introduced in driver version	Notes
db2.jcc.alternateUTF8Encoding		3.70, 4.70	"4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.apiKey	apiKey	4.24	"6" on page 294
db2.jcc.charOutputSize	charOutputSize	2.9	"1" on page 294, "5" on page 294, "4" on page 294
db2.jcc.clientApplcompat	clientApplcompat	4.24	"1" on page 294, "4" on page 294
db2.jcc.override.clientApplcompat	clientApplcompat	4.24	"2" on page 294, "4" on page 294
db2.jcc.currentPackageSet	currentPackageSet	4.26.14	"1" on page 294, "4" on page 294
db2.jcc.overrride.currentPackageSet	currentPackageSet	4.26.14	"2" on page 294, "4" on page 294
db2.jcc.currentSchema	currentSchema	1.2	"1" on page 294, "4" on page 294, "6" on page 294
db2.jcc.override.currentSchema	currentSchema	1.2	"2" on page 294, "4" on page 294, "6" on page 294
db2.jcc.currentSQLID	currentSQLID	1.3	"1" on page 294, "4" on page 294
db2.jcc.override.currentSQLID	currentSQLID	1.3	"2" on page 294, "4" on page 294
db2.jcc.customerId		4.29	"4" on page 294, "6" on page 294
db2.jcc.decimalRoundingMode	decimalRoundingMode	3.4	"1" on page 294, "4" on page 294, "6" on page 294
db2.jcc.override.decimalRoundingMode	decimalRoundingMode	3.4	"2" on page 294, "4" on page 294, "6" on page 294
db2.jcc.defaultSQLState		3.52, 4.2	"4" on page 294
db2.jcc.diagLevelExceptionCode		3.69, 4.19	"4" on page 294, "6" on page 294
db2.jcc.disableClientInputDataConversion	disableClientInputDataConversion	4.32	"1" on page 294, "6" on page 294
db2.jcc.override.disableClientInputDataConversion	disableClientInputDataConversion	4.32	"2" on page 294, "6" on page 294
db2.jcc.disableSQLJProfileCaching		1.8	"4" on page 294
db2.jcc.disableTimezone		3.68, 4.18	"4" on page 294
db2.jcc.dumpPool	dumpPool	3.52, 4.2	"1" on page 294, "3" on page 294, "4" on page 294, "5" on page 294
db2.jcc.dumpPoolStatisticsOnSchedule	dumpPoolStatisticsOnSchedule	3.52, 4.2	"1" on page 294, "3" on page 294, "4" on page 294, "5" on page 294

Table 42. Summary of Configuration properties and corresponding Connection and DataSource properties (continued)

Configuration property name	Connection or DataSource property name	Introduced in driver version	Notes
db2.jcc.dumpPoolStatisticsOnScheduleFile	dumpPoolStatisticsOnScheduleFile	3.52, 4.2	"1" on page 294, "3" on page 294, "4" on page 294, "5" on page 294
db2.jcc.enableDualTransportUsingDifferentProcess	enableDualTransportUsingDifferentProcess	4.31	"6" on page 294
db2.jcc.override.enableDualTransportUsingDifferentProcess	enableDualTransportUsingDifferentProcess	4.31	"2" on page 294, "6" on page 294
db2.jcc.enableInetAddressGetHostName		3.63, 4.13	"4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.enableMultirowInsertSupport	enableMultirowInsertSupport	3.62, 4.12	"2" on page 294, "4" on page 294
db2.jcc.enableRemoteLogging		4.29	"4" on page 294, "6" on page 294
db2.jcc.enableSeamlessFailoverErrorCodes	enableSeamlessFailoverErrorCodes	4.32	"1" on page 294, "4" on page 294
db2.jcc.override.enableSeamlessFailoverErrorCodes	enableSeamlessFailoverErrorCodes	4.32	"2" on page 294, "4" on page 294
db2.jcc.enableSysplexWLB	enableSysplexWLB	4.29	"1" on page 294, "4" on page 294, "6" on page 294
db2.jcc.override.enableSysplexWLB	enableSysplexWLB	4.29	"2" on page 294, "4" on page 294, "6" on page 294
db2.jcc.enableT2zosLBF	enableT2zosLBF	3.61, 4.11	"1" on page 294, "4" on page 294
db2.jcc.override.enableT2zosLBF	enableT2zosLBF	3.61, 4.11	"2" on page 294, "4" on page 294
db2.jcc.enableT2zosLBFSPResultSets	enableT2zosLBFSPResultSets	3.63, 4.13	"1" on page 294, "4" on page 294
db2.jcc.override.enableT2zosLBFSPResultSets	enableT2zosLBFSPResultSets	3.63, 4.13	"2" on page 294, "4" on page 294
db2.jcc.enableT2zosLBFSwitchWithIDAA		4.27	"4" on page 294
db2.jcc.encryptionAlgorithm	encryptionAlgorithm	3.65, 4.15	"1" on page 294, "4" on page 294, "6" on page 294
db2.jcc.override.encryptionAlgorithm	encryptionAlgorithm	3.65, 4.15	"2" on page 294, "4" on page 294, "6" on page 294
db2.jcc.extendedTableInfo	extendedTableInfo	3.69, 4.19	"1" on page 294, "4" on page 294
db2.jcc.jmxEnabled		4.0	"4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.indexName		4.29	"4" on page 294, "6" on page 294
db2.jcc.instanceId		4.29	"4" on page 294, "6" on page 294
db2.jcc.keyword		4.29	"4" on page 294, "6" on page 294

Table 42. Summary of Configuration properties and corresponding Connection and DataSource properties (continued)

Configuration property name	Connection or DataSource property name	Introduced in driver version	Notes
db2.jcc.lobOutputSize		1.8	“4” on page 294
db2.jcc.maxConnCachedParamBufferSize	maxConnCachedParamBufferSize	3.63, 4.13	“1” on page 294, “4” on page 294
db2.jcc.maxRefreshInterval		3.58, 4.8	“4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.maxTransportObjectIdleTime		3.52, 4.2	“1” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.maxTransportObjectWaitTime		3.52, 4.2	“1” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.maxTransportObjects	maxTransportObjects	2.6	“1” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.minTransportObjects		3.52, 4.2	“1” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.onDataTruncation	onDataTruncation	4.33	“1” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.override.onDataTruncation	onDataTruncation	4.33	“2” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.outputDirectory		3.61, 4.11	“6” on page 294
db2.jcc.pkList	pkList	1.4	“1” on page 294, “4” on page 294
db2.jcc.planName	planName	1.4	“1” on page 294, “4” on page 294
db2.jcc.progressiveStreaming	progressiveStreaming	3.0	“1” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.override.progressiveStreaming	progressiveStreaming	3.0	“2” on page 294, “4” on page 294, “5” on page 294, “6” on page 294
db2.jcc.queryPrefetch	queryPrefetch	4.29	“1” on page 294, “4” on page 294, “6” on page 294
db2.jcc.override.queryPrefetch	queryPrefetch	4.29	“2” on page 294, “4” on page 294, “6” on page 294
db2.jcc.remoteLoggingUrl		4.29	“4” on page 294, “6” on page 294
db2.jcc.rollbackOnShutdown		3.50, 4.0	“4” on page 294

Table 42. Summary of Configuration properties and corresponding Connection and DataSource properties (continued)

Configuration property name	Connection or DataSource property name	Introduced in driver version	Notes
db2.jcc.securityMechanism	securityMechanism	3.65, 4.15	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.securityMechanism	securityMechanism	3.65, 4.15	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.sendCharInputsUTF8	sendCharInputsUTF8	3.50, 4.0	"4" on page 294
db2.jcc.sqljStmtCacheSize		3.66, 4.16	"4" on page 294
db2.jcc.sqljToolsExitJVMOnCompletion		3.62, 4.12	"4" on page 294, "6" on page 294
db2.jcc.sqljUncustomizedWarningOrException		2.2	"4" on page 294, "6" on page 294
db2.jcc.ssid	ssid	3.6	"1" on page 294, "4" on page 294
db2.jcc.sslCertLocation	sslCertLocation	3.69, 4.19	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.sslCertLocation	sslCertLocation	3.69, 4.19	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.sslClientHostnameValidation	sslClientHostnameValidation	4.29	"1" on page 294, "4" on page 294, "6" on page 294
db2.jcc.override.sslClientHostnameValidation	sslClientHostnameValidation	4.29	"2" on page 294, "4" on page 294, "6" on page 294
db2.jcc.sslConnection	sslConnection	3.66, 4.16	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.sslConnection	sslConnection	3.66, 4.16	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.sslKeyStoreLocation	sslKeyStoreLocation	4.23	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.sslKeyStoreLocation	sslKeyStoreLocation	4.23	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.sslKeyStorePassword	sslKeyStorePassword	4.23	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.sslKeyStorePassword	sslKeyStorePassword	4.23	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294

Table 42. Summary of Configuration properties and corresponding Connection and DataSource properties (continued)

Configuration property name	Connection or DataSource property name	Introduced in driver version	Notes
db2.jcc.sslKeyStoreType	sslKeyStoreType	4.23	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.sslKeyStoreType	sslKeyStoreType	4.23	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.sslTrustStoreLocation	sslTrustStoreLocation	3.66, 4.16	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.sslTrustStoreLocation	sslTrustStoreLocation	3.66, 4.16	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.sslTrustStorePassword	sslTrustStorePassword	3.66, 4.16	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.sslTrustStorePassword	sslTrustStorePassword	3.66, 4.16	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.traceDirectory	traceDirectory	1.5	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.traceDirectory	traceDirectory	1.5	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.traceFile	traceFile	1.1	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.traceFile	traceFile	1.1	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.traceFileAppend	traceFileAppend	1.2	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.traceFileAppend	traceFileAppend	1.2	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.traceFileCount	traceFileCount	3.63, 4.13	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.traceFileSize	traceFileSize	3.63, 4.13	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294

Table 42. Summary of Configuration properties and corresponding Connection and DataSource properties (continued)

Configuration property name	Connection or DataSource property name	Introduced in driver version	Notes
db2.jcc.traceLevel	traceLevel	3.51, 4.1	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.override.traceLevel	traceLevel	3.51, 4.1	"2" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.traceOption	traceOption	3.63, 4.13	"1" on page 294, "4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.tracePolling		3.51, 4.1	"4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.tracePollingInterval		3.51, 4.1	"4" on page 294, "5" on page 294, "6" on page 294
db2.jcc.t2zosTraceFile		3.51, 4.1	"4" on page 294
db2.jcc.t2zosTraceBufferSize		3.51, 4.1	"4" on page 294
db2.jcc.t2zosTraceWrap		3.51, 4.1	"4" on page 294
db2.jcc.useCcsid420ShapedConverter		3.2	"4" on page 294
db2.jcc.useClientSideLicenseFirst	useClientSideLicenseFirst	4.29	"1" on page 294, "4" on page 294, "7" on page 294, "8" on page 294
db2.jcc.override.useClientSideLicenseFirst	useClientSideLicenseFirst	4.29	"2" on page 294, "4" on page 294, "7" on page 294, "8" on page 294

Note:

1. The `Connection` or `DataSource` property setting overrides the configuration property setting. The configuration property provides a default value for the `Connection` or `DataSource` property.
2. The configuration property setting overrides the `Connection` or `DataSource` property.
3. The corresponding Connection or DataSource property is defined only for IBM Informix.
4. The configuration property applies to Db2 for z/OS.
5. The configuration property applies to IBM Informix.
6. The configuration property applies to Db2 on Linux, UNIX, and Windows systems.
7. The configuration property applies to Db2 for IBM i.
8. The configuration property applies to Db2 on Cloud.

The following definitions describe the meanings of the configuration properties:

db2.jcc.accessToken
Identifies the token that is used for authentication at the server. Specifying an access token is valid only if property securityMechanism is set to TOKEN_SECURITY. The data type of this property is String. The maximum length of db2.jcc.accessToken is 8000 bytes.

If db2.jcc.accessToken is specified, property accessTokenType must also be specified. db2.jcc.accessToken cannot be specified when property user or property apiKey is also specified.

This property applies only to SSL connections. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems.

db2.jcc.accessTokenType
Identifies the type of access token that is specified in configuration, Connection, or DataSource property accessToken. The token type must be supported by the server. Specifying an access token type is valid only if property securityMechanism is set to TOKEN_SECURITY. The data type of this property is String. The maximum length of db2.jcc.accessToken is 255 bytes.

This property applies only to SSL connections. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems.

db2.jcc.accountingInterval
Specifies whether Db2 accounting records are produced at commit points or on termination of the physical connection to the data source. If the value of db2.jcc.accountingInterval is COMMIT, Db2 accounting records are produced at commit points. The property is illustrated in the following example:

```
db2.jcc.accountingInterval=COMMIT
```

Otherwise, accounting records are produced on termination of the physical connection to the data source.

db2.jcc.accountingInterval applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. db2.jcc.accountingInterval is not applicable to connections under CICS or IMS, or for Java stored procedures.

You can override db2.jcc.accountingInterval by setting the `accountingInterval` property for a `Connection` or `DataSource` object.

This configuration property applies only to Db2 for z/OS.

db2.jcc.allowSqljDuplicateStaticQueries
Specifies whether multiple open iterators on a single SELECT statement in an SQLJ application are allowed under IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

To enable this support, set db2.jcc.allowSqljDuplicateStaticQueries to YES or true.

db2.jcc.alternateUTF8Encoding
Specifies whether the JDBC driver that runs under IBM JRE Version 8 and above uses the UTF8J implementation in place of UTF8, when working with UTF8 data. Java 8 enforces stricter UTF8 implementation rules that might cause malformed input exceptions to occur with certain data, when upgrading to Java 8. The UTF8J implementation available in IBM JRE is expected to be compatible with prior versions of Java 8 UTF8 implementation that allows such data to be processed successfully with IBM JRE 8 and above.

0
Default value that means use the standard UTF8 implementation that is provided by the JRE for UTF8 data.

1
Value that means use UTF8J implementation for UTF8 data, if running under IBM JRE.

db2.jcc.apiKey
Identifies the API key that is used for authentication at the server. Specifying an API key is valid only if the securityMechanism property is set to PLUGIN_SECURITY. The data type of this property is String. The maximum length of db2.jcc.apiKey is 8000 bytes.

db2.jcc.apiKey cannot be specified when property user or property accessToken is also specified.

This property applies only to SSL connections. This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems.

db2.jcc.charOutputSize
Specifies the maximum number of bytes to use for INOUT or OUT stored procedure parameters that are registered as `Types.CHAR`.

Because DESCRIBE information for stored procedure INOUT and OUT parameters is not available at run time, by default, the IBM Data Server Driver for JDBC and SQLJ sets the maximum length of

each character INOUT or OUT parameter to 32767. For stored procedures with many Types.CHAR parameters, this maximum setting can result in allocation of much more storage than is necessary.

To use storage more efficiently, set db2.jcc.charOutputSize to the largest expected length for any Types.CHAR INOUT or OUT parameter.

db2.jcc.charOutputSize has no effect on INOUT or OUT parameters that are registered as Types.VARCHAR or Types.LONGVARCHAR. The driver uses the default length of 32767 for Types.VARCHAR and Types.LONGVARCHAR parameters.

When choosing the value for db2.jcc.charOutputSize take into account the possibility of expansion during character conversion. Because the IBM Data Server Driver for JDBC and SQLJ has no information about the server-side CCSID that is used for output parameter values, the driver requests the stored procedure output data in UTF-8 Unicode. The db2.jcc.charOutputSize value needs to be the maximum number of bytes that are needed after the parameter value is converted to UTF-8 Unicode. UTF-8 Unicode characters can require up to 3 bytes. (The euro symbol is an example of a 3-byte UTF-8 character). To ensure that the value of db2.jcc.charOutputSize is large enough, if you have no information about the output data, set db2.jcc.charOutputSize to three times the defined length of the largest CHAR parameter.

This configuration property applies only to Db2 for z/OS.

db2.jcc.clientApplcompat or db2.jcc.override.clientApplcompat
Allows the IBM Data Server Driver for JDBC and SQLJ to use the capabilities of a specified Db2 for z/OS function level. This configuration property applies only to Db2 for z/OS.

db2.jcc.currentPackageSet or db2.jcc.override.currentPackageSet
Specifies the collection ID to search for JDBC and SQLJ packages. The data type of this property is String. The default is NULLID. If this property value is set, its value overrides the value of jdbcCollection.

Multiple instances of the IBM Data Server Driver for JDBC and SQLJ can be installed at a database server by running the DB2Binder utility multiple times. The DB2binder utility includes a -collection option that lets the installer specify the collection ID for each IBM Data Server Driver for JDBC and SQLJ instance. To choose an instance of the IBM Data Server Driver for JDBC and SQLJ for a connection, specify a currentPackageSet value that matches the collection ID for one of the IBM Data Server Driver for JDBC and SQLJ instances.

The precedence rules for the currentPackagePath and currentPackageSet properties follow the precedence rules for the CURRENT PACKAGESET and CURRENT PACKAGE PATH special registers.

This configuration property applies only to Db2 for z/OS.

db2.jcc.currentSchema or db2.jcc.override.currentSchema
Specifies the default schema name that is used to qualify unqualified database objects in dynamically prepared SQL statements. This value of this property sets the value in the CURRENT SCHEMA special register on the database server. The schema name is case-sensitive, and must be specified in uppercase characters.

This configuration property applies only to Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems.

db2.jcc.currentSQLID or db2.jcc.override.currentSQLID
The properties specify the following statements:

- The authorization ID that is used for authorization checking on dynamically prepared CREATE, GRANT, and REVOKE SQL statements.
- The owner of a table space, database, storage group, or synonym that is created by a dynamically issued CREATE statement.
- The implicit qualifier of all table, view, alias, and index names specified in dynamic SQL statements.

currentSQLID sets the value in the CURRENT SQLID special register on a Db2 for z/OS server. If the currentSQLID property is not set, the default schema name is the value in the CURRENT SQLID special register.

This configuration property applies only to Db2 for z/OS.

db2.jcc.customerId
Specifies a customer ID value that is sent with IBM Data Server Driver for JDBC and SQLJ trace output to a search and analytics product, such as Elasticsearch. The default value for db2.jcc.customerId is cid.

db2.jcc.decimalRoundingMode or db2.jcc.override.decimalRoundingMode
Specifies the rounding mode for assignment to decimal floating-point variables or DECFLOAT columns on Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems data servers.

The following includes possible values of the properties:

com.ibm.db2.jcc.DB2BaseDataSource.ROUND_DOWN (1)
Rounds the value towards 0 (truncation). The discarded digits are ignored.

com.ibm.db2.jcc.DB2BaseDataSource.ROUND_CEILING (2)
Rounds the value towards positive infinity. If all of the discarded digits are zero or if the sign is negative, the result is unchanged other than the removal of the discarded digits. Otherwise, the result coefficient is incremented by 1.

com.ibm.db2.jcc.DB2BaseDataSource.ROUND_HALF_EVEN (3)
Rounds the value to the nearest value; if the values are equidistant, rounds the value so that the final digit is even. If the discarded digits represent greater than half (0.5) of the value of one in the next left position, then the result coefficient is incremented by 1. If they represent less than half, then the result coefficient is not adjusted (that is, the discarded digits are ignored). Otherwise, the result coefficient is unaltered if its rightmost digit is even, or is incremented by 1 if its rightmost digit is odd (to make an even digit).

com.ibm.db2.jcc.DB2BaseDataSource.ROUND_HALF_UP (4)
Rounds the value to the nearest value; if the values are equidistant, rounds the value away from zero. If the discarded digits represent greater than or equal to half (0.5) of the value of one in the next left position, then the result coefficient is incremented by 1. Otherwise, the discarded digits are ignored.

com.ibm.db2.jcc.DB2BaseDataSource.ROUND_FLOOR (6)
Rounds the value towards negative infinity. If all of the discarded digits are zero or if the sign is positive, the result is unchanged other than the removal of discarded digits. Otherwise, the sign is negative and the result coefficient is incremented by 1.

com.ibm.db2.jcc.DB2BaseDataSource.ROUND_UNSET (-2147483647)
No rounding mode was explicitly set. The IBM Data Server Driver for JDBC and SQLJ does not use the decimalRoundingMode to set the rounding mode on the database server. The rounding mode is ROUND_HALF_EVEN.

If you explicitly set the db2.jcc.decimalRoundingMode or db2.jcc.override.decimalRoundingMode value, that value updates the CURRENT DECFLOAT ROUNDING MODE special register value on a Db2 for z/OS data server.

If you explicitly set the db2.jcc.decimalRoundingMode or db2.jcc.override.decimalRoundingMode value, that value does not update the CURRENT DECFLOAT ROUNDING MODE special register value on a Db2 on Linux, UNIX, and Windows systems data server. If the value to which you set db2.jcc.decimalRoundingMode or db2.jcc.override.decimalRoundingMode is not the same as the value of the CURRENT DECFLOAT ROUNDING MODE special register, an `Exception` is thrown. To change the data server value, you need to set that value with the decflt_rounding database configuration parameter.

decimalRoundingMode does not affect decimal value assignments. The IBM Data Server Driver for JDBC and SQLJ always rounds decimal values down.

db2.jcc.defaultSQLState
Specifies the SQLSTATE value that the IBM Data Server Driver for JDBC and SQLJ returns to the client for `SQLException` or `SQLWarning` objects that have null SQLSTATE values. This configuration property can be specified in the following ways:

db2.jcc.defaultSQLState
If db2.jcc.defaultSQLState is specified with no value, the IBM Data Server Driver for JDBC and SQLJ returns 'FFFFF'.

db2.jcc.defaultSQLState=*xxxxx*
The value *xxxxx* in the format is the value that the IBM Data Server Driver for JDBC and SQLJ returns when the SQLSTATE value is null. If *xxxxx* is longer than 5 bytes, the driver truncates the value to 5 bytes. If *xxxxx* is shorter than 5 bytes, the driver pads *xxxxx* on the right with blanks.

If db2.jcc.defaultSQLState is not specified, the IBM Data Server Driver for JDBC and SQLJ returns a null SQLSTATE value.

This configuration property applies only to Db2 for z/OS.

db2.jcc.diagLevelExceptionCode
Specifies one or more SQL error codes or SQL warning codes for which diagnostic information is collected.

If a value of db2.jcc.diagLevelExceptionCode is not specified, no diagnostic data is collected.

If db2.jcc.diagLevelExceptionCode is set to -1, diagnostic information is collected for all SQL error codes.

An SQL error code can be specified without a sign, prefixed by a minus (-) sign, or suffixed by the letter n. An SQL warning code can be prefixed by a plus (+) sign, or suffixed by the letter p.

When more than one SQL error code or SQL warning code is specified, the codes must be separated by commas.

Examples:

To collect diagnostic information for SQL error code -204, specify one of the following values:

- db2.jcc.diagLevelExceptionCode=204
- db2.jcc.diagLevelExceptionCode=-204
- db2.jcc.diagLevelExceptionCode=204n

To collect diagnostic information for SQL warning code +222, specify one of the following values:

- db2.jcc.diagLevelExceptionCode=+222
- db2.jcc.diagLevelExceptionCode=222p

Some examples of specifying collection of diagnostic information for SQL error codes -204, -30108, and -4499 are:

- db2.jcc.diagLevelExceptionCode=-204,-30108,-4499
- db2.jcc.diagLevelExceptionCode=204,30108n,4499
- db2.jcc.diagLevelExceptionCode=204n,30108,4499n

Some examples of specifying collection of diagnostic information for SQL error code -30108 and SQL warning codes +100 and +222 are:

- db2.jcc.diagLevelExceptionCode=+100,-30108,222p
- db2.jcc.diagLevelExceptionCode=100p,30108,+222

The diagnostic data is written to a file in the directory that is specified by configuration property db2.jcc.outputDirectory. The format of the file is:

```
jccDump_timestamp_random-number_i.log
```

- *timestamp* is the timestamp when the data is written.
- *random-number* is a randomly generated positive integer.
- *i* is 0 or 1.

db2.jcc.disableClientInputDataConversion or db2.jcc.override.disableClientInputDataConversion
Specifies whether the IBM Data Server Driver for JDBC and SQLJ converts certain types of numeric client data before sending the data to a Db2 on Linux, UNIX, and Windows systems data server.

The affected source and target data types are listed in NUMBER data type. For information on mappings between Java data types and data server data types, see "Data types that map to database data types in Java applications" on page 207.

Disabling conversion might be necessary when the DB2_COMPATIBILITY_VECTOR registry variable on the data server is set to X'10'.

Possible values are:

0 or not specified
Specifies that the IBM Data Server Driver for JDBC and SQLJ converts the client data to the target data type. 0 is the default.

1
Specifies that the IBM Data Server Driver for JDBC and SQLJ does not convert the client data to the target data type.

2
Specifies that the IBM Data Server Driver for JDBC and SQLJ converts the client data to the target data type.

db2.jcc.disableSQLJProfileCaching
Specifies whether serialized profiles are cached when the JVM under which their application is running is reset. db2.jcc.disableSQLJProfileCaching applies only to applications that run in a resettable JVM (applications that run in the CICS, IMS, or Java stored procedure environment), and use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. The following illustrates possible values of the property:

YES
SQLJ serialized profiles are not cached every time the JVM is reset so that new versions of the serialized profiles are loaded when the JVM is reset. Use this option when an application is under development, and new versions of the application and its serialized profiles are produced frequently.

NO
SQLJ serialized profiles are cached when the JVM is reset. NO is the default.

This configuration property applies only to Db2 for z/OS.

db2.jcc.disableTimezone
Specifies whether the time zone portion of a timestamp value is not sent to the data server. The following values show possible values of the property:

true or yes
Indicates that the time zone portion of a timestamp is not sent to the data server, even if the data server supports the TIMESTAMP WITH TIME ZONE data type.

Any other value
Default value that indicates that the time zone portion of a timestamp is sent to the data server.

db2.jcc.dumpPool
Specifies the types of statistics on global transport pool events that are written, in addition to summary statistics. The global transport pool is used for the connection concentrator and sysplex workload balancing.

db2.jcc.dumpPoolStatisticsOnSchedule and db2.jcc.dumpPoolStatisticsOnScheduleFile must also be set for writing statistics before any statistics are written.

The following list illustrates types of statistics with the db2.jcc.dumpPool property, that you can specify one or more of:

- `DUMP_REMOVE_OBJECT` (hexadecimal: X'01', decimal: 1)
- `DUMP_GET_OBJECT` (hexadecimal: X'02', decimal: 2)

- DUMP_WAIT_OBJECT (hexadecimal: X'04', decimal: 4)
- DUMP_SET_AVAILABLE_OBJECT (hexadecimal: X'08', decimal: 8)
- DUMP_CREATE_OBJECT (hexadecimal: X'10', decimal: 16)
- DUMP_SYSPLEX_MSG (hexadecimal: X'20', decimal: 32)
- DUMP_POOL_ERROR (hexadecimal: X'80', decimal: 128)

To trace more than one type of event, add the values for the types of events that you want to trace. For example, suppose that you want to trace DUMP_GET_OBJECT and DUMP_CREATE_OBJECT events. The numeric equivalents of these values are 2 and 16, so you specify 18 for the db2.jcc.dumpPool value.

The default is 0, which means that only summary statistics for the global transport pool are written.

This configuration property applies only to Db2 for z/OS or IBM Informix.

db2.jcc.dumpPoolStatisticsOnSchedule
Specifies how often, in seconds, global transport pool statistics are written to the file that is specified by db2.jcc.dumpPoolStatisticsOnScheduleFile. The global transport object pool is used for the connection concentrator and sysplex workload balancing.

The default is -1. -1 means that global transport pool statistics are not written.

This configuration property applies only to Db2 for z/OS or IBM Informix.

db2.jcc.dumpPoolStatisticsOnScheduleFile
Specifies the name of the file to which global transport pool statistics are written. The global transport pool is used for the connection concentrator and sysplex workload balancing.

If db2.jcc.dumpPoolStatisticsOnScheduleFile is not specified, global transport pool statistics are not written.

This configuration property applies only to Db2 for z/OS or IBM Informix.

db2.jcc.enableInetAddressGetHostName
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses the `InetAddress.getHostName` and `InetAddress.getCanonicalHostName` methods to determine the host name for an IP address. db2.jcc.enableInetAddressGetHostName applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. Possible values of the property include the following values:

true
The IBM Data Server Driver for JDBC and SQLJ uses the `InetAddress.getHostName` and `InetAddress.getCanonicalHostName` methods to determine the host name for an IP address.

When you specify `true`, applications might take longer to run because of the additional time that is required for DNS lookup operations.

false
The IBM Data Server Driver for JDBC and SQLJ uses the `InetAddress.getHostAddress` method to return the IP address. The returned IP address is used in place of the host name.

For versions 3.65 and 4.15 or later of the IBM Data Server Driver for JDBC and SQLJ, the default is `false`. For versions 3.64 and 4.14 or earlier, the default is `true`.

db2.jcc.enableDualTransportUsingDifferentProcess or db2.jcc.override.enableDualTransportUsingDifferentProcess
Specifies the protocol that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use for a dual transport or multi-transport transaction model. The possible values are:

0 or not specified
Specifies that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use a protocol in which the Java runtime environment does not free Xid objects after an xa_end call. The objects are available until an xa_commit or xa_rollback call is issued. This value is the default.

1
Specifies that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use a protocol in which the Java runtime environment frees Xid objects after an xa_end call. An application might need to set this value for transaction managers that use the IBM Data Server Driver for JDBC and SQLJ to issue xa_start and xa_end calls, but use some other means to issue xa_prepare, xa_commit, or xa_rollback calls. An example of such a transaction manager is IBM MQ.

The behavior for a property value of 1 takes effect only when the xaNetworkOptimization property and the enableSysplexWLB property are set to `false`.

2
Specifies that XA transactions under the IBM Data Server Driver for JDBC and SQLJ use a protocol in which the Java runtime environment does not free Xid objects after an xa_end call. The objects are available until an xa_commit or xa_rollback call is issued. This value is the default.

db2.jcc.override.enableMultiRowInsertSupport
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses multi-row INSERT for batched INSERT or MERGE operations, when the target data server is a Db2 for z/OS server that supports multi-row INSERT. The batch operations must be `PreparedStatement` calls with parameter markers. The default is `true`.

db2.jcc.override.enableMultiRowInsertSupport must be set to `false` if INSERT FROM SELECT statements are executed in a batch. Otherwise, the driver throws a `BatchUpdateException`.

Possible values are:

true
Specifies the default value that the IBM Data Server Driver for JDBC and SQLJ uses multi-row INSERT for batched INSERT or MERGE operations, when the target data server is a Db2 for z/OS server that supports multi-row INSERT.

false
Specifies that the IBM Data Server Driver for JDBC and SQLJ does not use multi-row INSERT for batched INSERT or MERGE operations, when the target data server is a Db2 for z/OS server that supports multi-row INSERT.

db2.jcc.enableRemoteLogging
Specifies whether the IBM Data Server Driver for JDBC and SQLJ sends trace output to Elasticsearch or an equivalent search and analytics product.

Possible values are:

true
Specifies that IBM Data Server Driver for JDBC and SQLJ trace output is sent to a search and analytics product, such as Elasticsearch. The product must be configured to receive and process the trace output.

false
Specifies that IBM Data Server Driver for JDBC and SQLJ trace output is sent to a local file that is specified by driver properties, instead of a search and analytics product. `false` is the default.

db2.jcc.enableSeamlessFailoverErrorCodes or db2.jcc.override.enableSeamlessFailoverErrorCodes
Specifies whether the IBM Data Server Driver for JDBC and SQLJ maps seamless error codes, such as -4498, -30108, or -20542, to communication error code -4499. The data type of this property is Boolean. Possible values are:

true
The IBM Data Server Driver for JDBC and SQLJ does not map seamless errors to communication error code -4499. The application receives different error codes, depending on the types of errors that occurred.

false
The IBM Data Server Driver for JDBC and SQLJ maps seamless errors to communication error code -4499. If a seamless error occurs during execution of an application, the driver throws an exception with error code -4499. `false` is the default.

db2.jcc.enableSeamlessFailoverErrorCodes and db2.jcc.override.enableSeamlessFailoverErrorCodes apply to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS only.

db2.jcc.enableSysplexWLB or db2.jcc.override.enableSysplexWLB
Indicates whether the sysplex workload balancing function of the IBM Data Server Driver for JDBC and SQLJ is enabled.

Possible values are:

true
Specifies that the sysplex workload balancing function of the IBM Data Server Driver for JDBC and SQLJ is enabled.

false
Specifies that the sysplex workload balancing function of the IBM Data Server Driver for JDBC and SQLJ is disabled. `false` is the default.

For connections to Db2 on Linux, UNIX, and Windows systems, db2.jcc.enableSysplexWLB or db2.jcc.override.enableSysplexWLB can have a value of `true` only if the servers are in a pureScale environment. For other supported database products, db2.jcc.enableSysplexWLB or db2.jcc.override.enableSysplexWLB can have a value of `true` only if the servers have sysplex workload balancing enabled.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

db2.jcc.enableT2zosLBF or db2.jcc.override.enableT2zosLBF
Specifies whether limited block fetch can be used for connections that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to retrieve data from a table on a local Db2 for z/OS data server. Possible values are:

0 or not specified
This value is the default.

- For a connection to a Db2 for z/OS data server in Version 10 conversion mode, specifies that limited block fetch is not used for retrieving data from a local table that uses IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.
- For a connection to a Db2 for z/OS data server in Version 10 new-function mode or later, specifies that limited block fetch can be used for retrieving data from a local table that uses IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

1
Specifies that limited block fetch can be used when an application that is running under the IBM Data Server Driver for JDBC and SQLJ type 2 connectivity retrieves data from a local table.

If you set this property to 1, and IBM Db2 Analytics Accelerator for z/OS might also need to be switched on during cursor reuse, you need to set configuration property db2.jcc.enableT2zosLBFSwitchWithIDAA to 1.

2
Specifies that limited block fetch is not used for retrieving data from a local table that uses IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

db2.jcc.enableT2zosLBF and db2.jcc.override.enableT2zosLBF apply to Db2 for z/OS data servers in Version 10 new-function mode or later. These properties do not apply to retrieval of stored procedure result sets.

db2.jcc.enableT2zosLBFSPResultSets or db2.jcc.override.enableT2zosLBFSPResultSets
Specifies whether limited block fetch is used for connections that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to retrieve data from a stored procedure result set on a local Db2 for z/OS data server. Possible values are:

0 or 1
Specifies the default value that limited block fetch is used for retrieving data from a stored procedure result set by using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

2
Specifies that limited block fetch is not used for retrieving data from a stored procedure result set by using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

db2.jcc.enableT2zosLBFSPResultSets and db2.jcc.override.enableT2zosLBFSPResultSets apply to Db2 for z/OS data servers in Version 10 new-function mode or later.

db2.jcc.enableT2zosLBFSwitchWithIDAA
Specifies when limited block fetch can be used for applications that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to run on data servers that use IBM Db2 Analytics Accelerator for z/OS. The driver uses this property only if db2.jcc.enableT2zosLBF is set to 1. Possible values are:

0 or not specified
This value is the default.

Specifies that when IBM Db2 Analytics Accelerator for z/OS is not available or stopped, Db2 for z/OS can use limited block fetch when a Java application uses a local cursor to retrieve data.

1
Specifies that IBM Db2 Analytics Accelerator for z/OS might be switched on or off when applications are running under the IBM Data Server Driver for JDBC and SQLJ. When IBM Db2 Analytics Accelerator for z/OS is active, a remote cursor is activated, and limited block fetch is disabled.

db2.jcc.encryptionAlgorithm or db2.jcc.override.encryptionAlgorithm
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses 56-bit DES (weak) encryption or 256-bit AES (strong) encryption.

db2.jcc.encryptionAlgorithm or db2.jcc.override.encryptionAlgorithm can be specified only if property db2.jcc.securityMechanism or property securityMechanism is set to 7 or 9.

Possible values of the properties include the following values:

1
The driver uses 56-bit DES encryption.

2
The driver uses 256-bit AES encryption, if the database server supports it. 256-bit AES encryption is available for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

For AES encryption, you need an unrestricted policy file for JCE. That file is available at the following location:

```
https://www.ibm.com/marketing/iwm/iwm/web/preLogin.do?source=jcesdk
```

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default encryption algorithm is 256-bit AES encryption (2).

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default encryption algorithm is 56-bit DES encryption (1).

db2.jcc.encryptionAlgorithm can be specified only if the db2.jcc.securityMechanism, db2.jcc.override.securityMechanism, or securityMechanism value is set for encrypted password security or encrypted user ID and password security.

db2.jcc.extendedTableInfo
Specifies whether information about extended table types is returned from a `DatabaseMetaData.getTables` method call. Currently, one extended table type exists: ACCEL-ONLY TABLE.

0
The result set that is returned by the `DatabaseMetaData.getTables` method does not contain columns for extended table types.

Rows for extended table types are returned only if "TABLE" is explicitly specified in the *types* parameter value. In this case, extended table types are listed as TABLE in the TABLE_TYPE column of the result set.

1

The result set that is returned by the `DatabaseMetaData.getTables` method contains rows and columns for extended table types. In particular:

- The result set contains these extra columns after the columns that are always returned in the result set from `DatabaseMetaData.getTables`:

Table 43. Extra columns returned by `DatabaseMetaData.getTables`

Column Name	Data type	Description
TEMPORAL_TABLE_TYPE	String	Contains the type of temporal table. The following shows possible values of the temporal table: **SYSTEM** System-period temporal table. **APPLICATION** Application-period temporal table. **BITEMPORAL** Bitemporal table. **Empty string** Not a temporal table. This row is returned for connections to Db2 for z/OS Version 10 or later.
IS_ACCELERATED	String	Indicates whether the table is an accelerated table. Possible values are YES or NO. This row is returned for connections to Db2 for z/OS Version 10 or later.
ACCEL_ARCHIVE_STATUS	String	Contains the archive status of the table in the accelerator database. See the description of the ARCHIVE column in SYSACCEL.SYSACCELERATEDTABLES table (Db2 SQL) for the possible values and their meanings. This row is returned for connections to Db2 for z/OS Version 10 or later.
IS_ARCHIVE_ENABLED	String	Indicates whether the table is an archive-enabled table. Possible values are YES or NO. This row is returned for connections to Db2 for z/OS Version 11 or later.

- Rows for extended table types are returned under the following circumstances:
  - All table types are implicitly requested by specifying null in the *types* parameter value.
  - An extended table type name is explicitly specified in the *types* parameter value.

    In this case, the extended table type is listed by its extended table type name in the TABLE_TYPE column of the result set.

db2.jcc.indexName
Specifies the name of an index in which the IBM Data Server Driver for JDBC and SQLJ trace output is stored in a search and analytics product, such as Elasticsearch. The default value for db2.jcc.indexName is jcc.

db2.jcc.instanceId
Specifies a name for an instance configuration name in a search and analytics product, such as Elasticsearch. That name identifies the instance that is used for IBM Data Server Driver for JDBC and SQLJ trace output that is sent to the product. The default value for db2.jcc.instanceId is iid.

db2.jcc.jmxEnabled
Specifies whether the Java Management Extensions (JMX) is enabled for the IBM Data Server Driver for JDBC and SQLJ instance. JMX must be enabled before applications can use the remote trace controller.

Possible values of the property include the following values:

true or yes
Indicates that JMX is enabled.

Any other value
Indicates the default value that JMX is disabled.

db2.jcc.keyword
Specifies a keyword value that identifies the type of data that is in IBM Data Server Driver for JDBC and SQLJ trace output that is sent to a search and analytics product, such as Elasticsearch. The default value for db2.jcc.keyword is debug.

db2.jcc.lobOutputSize
Specifies the number of bytes of storage that the IBM Data Server Driver for JDBC and SQLJ needs to allocate for output LOB values when the driver cannot determine the size of those LOBs. This situation occurs for LOB stored procedure output parameters. db2.jcc.lobOutputSize applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

The default value for db2.jcc.lobOutputSize is 1048576. For systems with storage limitations and smaller LOBs, set the db2.jcc.lobOutputSize value to a lower number.

For example, if you know that the output LOB size is at most 64000, set db2.jcc.lobOutputSize to 64000.

This configuration property applies only to Db2 for z/OS.

db2.jcc.maxConnCachedParamBufferSize
Specifies the maximum size of an internal buffer that is used for caching input parameter values for `PreparedStatement` objects. The buffer caches values on the native code side that are passed from the driver's Java code side for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. The buffer is used by all `PreparedStatement` objects for a `Connection`. The default is 1048576 (1 MB). The default must be adequate for most users. Set db2.jcc.maxConnCachedParamBufferSize to a larger value if many applications that run under the driver instance have `PreparedStatement` objects with large numbers of input parameters or large input parameters. The db2.jcc.maxConnCachedParamBufferSize must be larger than the maximum size of all input parameter data for a `Connection`. However, you also need to consider the total number of connections and the maximum amount of memory that is available when you set the db2.jcc.maxConnCachedParamBufferSize value.

The buffer exists for the life of a `Connection`, unless it reaches the maximum specified size. If that happens, the buffer is freed on each call to the native code. The corresponding buffer on the Java code side is freed on `PreparedStatement.clearParameters` and `PreparedStatement.close` calls. The buffers are not cleared if an application calls `PreparedStatement.clearParameters`, and the buffers did not reach the maximum size.

db2.jcc.maxRefreshInterval
For workload balancing, specifies the maximum amount of time in seconds between refreshes of the client copy of the server list. The minimum valid value is 1.

For version 3.63 or 4.13 or later of the IBM Data Server Driver for JDBC and SQLJ, the default is 10 seconds. For earlier versions of the driver, the default is 30 seconds.

db2.jcc.maxTransportObjectIdleTime
Specifies the amount of time in seconds that an unused transport object stays in a global transport object pool before it can be deleted from the pool. Transport objects are used for the connection concentrator and sysplex workload balancing.

The default value for db2.jcc.maxTransportObjectIdleTime is 10. Setting db2.jcc.maxTransportObjectIdleTime to a value less than 0 causes unused transport objects to be deleted from the pool immediately. Setting the value below 0 this is **not** recommended because it can cause severe performance degradation.

db2.jcc.maxTransportObjects
Specifies the upper limit for the number of transport objects in a global transport object pool for the connection concentrator and sysplex workload balancing. When the number of transport objects in the pool reaches the db2.jcc.maxTransportObjects value, transport objects that have not been used for longer than the db2.jcc.maxTransportObjectIdleTime value are deleted from the pool.

For version 3.63 or 4.13 or later of the IBM Data Server Driver for JDBC and SQLJ, the default is 1000. For earlier versions of the driver, the default is -1.

Any value that is less than or equal to 0 means that no limit to the number of transport objects in the global transport object pool exists.

db2.jcc.maxTransportObjectWaitTime
Specifies the maximum amount of time in seconds that an application waits for a transport object if the db2.jcc.maxTransportObjects value is not reached yet. Transport objects are used for the connection concentrator and sysplex workload balancing. When an application waits for longer than the db2.jcc.maxTransportObjectWaitTime value, the global transport object pool throws an SQLException.

Any negative value means that applications wait forever.

For version 3.63 or 4.13 or later of the IBM Data Server Driver for JDBC and SQLJ, the default is 1 second. For earlier versions of the driver, the default is -1.

db2.jcc.minTransportObjects
Specifies the lower limit for the number of transport objects in a global transport object pool for the connection concentrator and sysplex workload balancing. When a JVM is created, no transport objects exist in the pool. Transport objects are added to the pool as they are needed. After the db2.jcc.minTransportObjects value is reached, the number of transport objects in the global transport object pool never goes below the db2.jcc.minTransportObjects value for the lifetime of that JVM.

The default value for db2.jcc.minTransportObjects is 0. Any value that is less than or equal to 0 means that the global transport object pool can become empty.

db2.jcc.onDataTruncation or db2.jcc.override.onDataTruncation
Specifies the action that the IBM Data Server Driver for JDBC and SQLJ takes when an input value is inserted into a column, and the value is too large for that column. db2.jcc.onDataTruncation and db2.jcc.override.onDataTruncation apply only to version 4.33 or later of the driver. Possible values are:

1
The IBM Data Server Driver for JDBC and SQLJ issues a warning if data truncation occurs. This value is the default.

2
The IBM Data Server Driver for JDBC and SQLJ throws an exception if data truncation occurs.

3
The IBM Data Server Driver for JDBC and SQLJ takes no action, which is the same as the behavior for driver versions before 4.33.

db2.jcc.outputDirectory
Specifies where the IBM Data Server Driver for JDBC and SQLJ stores temporary log files.

If this property is set, the IBM Data Server Driver for JDBC and SQLJ stores the following files in the specified directory:

jccdiag.log
Contains diagnostic information that is written by the IBM Data Server Driver for JDBC and SQLJ.

If db2.jcc.outputDirectory is not specified, the IBM Data Server Driver for JDBC and SQLJ searches for a directory that is specified by the java.io.tmpdir system property. If the java.io.tmpdir system property is also not specified, the driver does not write diagnostic information to jccdiag.log. If a directory is specified, but jccdiag.log cannot be accessed, the driver does not write diagnostic information to jccdiag.log.

The IBM Data Server Driver for JDBC and SQLJ does not create the directory. You must create the directory and assign the required file permissions.

db2.jcc.outputDirectory can specify an absolute path or a relative path. However, an absolute path is recommended.

db2.jcc.pkList
Specifies a package list that is used for the underlying RRSAF CREATE THREAD call when a JDBC or SQLJ connection to a data source is established. Specify this property if you do not bind plans for your SQLJ programs or for the JDBC driver. If you specify this property, **do not specify db2.jcc.planName.**

db2.jcc.pkList applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. db2.jcc.pkList does not apply to applications that run under CICS or IMS, or to Java stored procedures. The JDBC driver ignores the db2.jcc.pkList setting in those cases.

Recommendation: Use db2.jcc.pkList instead of db2.jcc.planName.

The format of the package list is:

The default value of db2.jcc.pkList is NULLID.*.

If you specify the **-collection** parameter when you run `com.ibm.db2.jcc.DB2Binder`, the collection ID that you specify for IBM Data Server Driver for JDBC and SQLJ packages when you run `com.ibm.db2.jcc.DB2Binder` must also be in the package list for the db2.jcc.pkList property.

You can override db2.jcc.pkList by setting the `pkList` property for a `Connection` or `DataSource` object.

The following example specifies a package list for a IBM Data Server Driver for JDBC and SQLJ instance whose packages are in collection JDBCCID. SQLJ applications that are prepared under this driver instance are bound into collections SQLJCID1, SQLJCID2, or SQLJCID3.

```
db2.jcc.pkList=JDBCCID.*,SQLJCID1.*,SQLJCID2.*,SQLJCID3.*
```

This configuration property applies only to Db2 for z/OS.

db2.jcc.planName
Specifies a Db2 for z/OS plan name that is used for the underlying RRSAF CREATE THREAD call when a JDBC or SQLJ connection to a data source is established. Specify this property if you bind plans for your SQLJ programs and for the JDBC driver packages. If you specify this property, **do not specify db2.jcc.pkList.**

db2.jcc.planName applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. db2.jcc.planName does not apply to applications that run under CICS or IMS, or to Java stored procedures. The JDBC driver ignores the db2.jcc.planName setting in those cases.

If you do not specify this property or the db2.jcc.pkList property, the IBM Data Server Driver for JDBC and SQLJ uses the db2.jcc.pkList default value of NULLID.*.

If you specify db2.jcc.planName, you need to bind the packages that you produce when you run `com.ibm.db2.jcc.DB2Binder` into a plan whose name is the value of this property. You also need to bind all SQLJ packages into a plan whose name is the value of this property.

You can override db2.jcc.planName by setting the `planName` property for a `Connection` or `DataSource` object.

The following example specifies a plan name of MYPLAN for the IBM Data Server Driver for JDBC and SQLJ JDBC packages and SQLJ packages.

```
db2.jcc.planName=MYPLAN
```

This configuration property applies only to Db2 for z/OS.

db2.jcc.progressiveStreaming or db2.jcc.override.progressiveStreaming
Specifies whether the JDBC driver uses progressive streaming when progressive streaming is supported on the data source.

With progressive streaming, the data source dynamically determines the most efficient mode in which to return LOB or XML data, based on the size of the LOBs or XML objects. Progressive streaming is also known as dynamic data format.

Valid values for the properties include the following values:

1
Use progressive streaming, if the data source supports it.

2
Do not use progressive streaming.

db2.jcc.queryPrefetch or db2.jcc.override.queryPrefetch
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses query prefetch behavior for retrieving rows from a Db2 table. Use of query prefetch can improve performance when an application retrieves large result sets. Query prefetch is not used when an application retrieves LOB or XML data, or when the cursor that is used for data retrieval is not a forward-only cursor.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

Possible values are:

true
Specifies that the IBM Data Server Driver for JDBC and SQLJ can use query prefetch when it retrieves rows from a table.

false
Specifies that the IBM Data Server Driver for JDBC and SQLJ does not use query prefetch when it retrieves rows from a table. `false` is the default.

db2.jcc.remoteLoggingUrl
Specifies the URL of the remote product to which IBM Data Server Driver for JDBC and SQLJ trace output is to be sent when db2.jcc.enableRemoteLogging is set to `true`. For example:

```
db2.jcc.remoteLoggingUrl=http://127.0.0.1:9200/
```

If the value of db2.jcc.remoteLoggingUrl is invalid or the URL cannot be reached, the driver sends the output to a local file that is specified by driver properties.

db2.jcc.rollbackOnShutdown
Specifies whether Db2 for z/OS forces a rollback operation and disables further operations on JDBC connections that are in a unit of work during processing of JVM shutdown hooks.

db2.jcc.rollbackOnShutdown applies to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity only.

db2.jcc.rollbackOnShutdown does not apply to the CICS, IMS, stored procedure, or WebSphere Application Server environments.

Valid values for the properties include the following values:

yes or true
The IBM Data Server Driver for JDBC and SQLJ directs Db2 for z/OS to force a rollback operation and disables further operations on JDBC connections that are in a unit of work during processing of JVM shutdown hooks.

Any other value
The default value that IBM Data Server Driver for JDBC and SQLJ takes no action with respect to rollback processing during processing of JVM shutdown hooks.

This configuration property applies only to Db2 for z/OS.

db2.jcc.securityMechanism or db2.jcc.override.securityMechanism
Specifies the DRDA security mechanism. Possible values are:

3
User ID and password

4
User ID only

7
User ID, encrypted password

9
Encrypted user ID and password

11
Kerberos. This value does not apply to connections to IBM Informix.

12
Encrypted user ID and encrypted security-sensitive data. This value applies to connections to Db2 for z/OS only.

13
Encrypted user ID and password, and encrypted security-sensitive data. This value does not apply to connections to IBM Informix.

15
Plug-in security. This value applies to connections to Db2 on Linux, UNIX, and Windows systems only.

16
Encrypted user ID. This value does not apply to connections to IBM Informix.

18
Client certificate security, that uses SSL. This value applies to connections to Db2 for z/OS only.

Important:

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default value for db2.jcc.securityMechanism is encrypted user ID and password security (9). If the data server does not support encrypted user ID and password security, but supports user ID and password security (3), the IBM Data Server Driver for JDBC and SQLJ driver changes the security mechanism to user ID and password security (3) and attempts to connect to the data server. The connection retry using user ID and password security (3) might cause a slight performance impact. Any other mismatch in security mechanism support between the requester and the data server results in an error.

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default value for db2.jcc.securityMechanism is user ID and password security (3). If the data server does not support user ID and password security, but supports encrypted user ID and password security (9), the IBM Data Server Driver for JDBC and SQLJ driver changes the security mechanism to encrypted user ID and password security and attempts to connect to the data server. Any other mismatch in security mechanism support between the requester and the data server results in an error.

This property does not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

db2.jcc.sendCharInputsUTF8

Specifies whether the IBM Data Server Driver for JDBC and SQLJ converts character input data to the CCSID of the Db2 for z/OS database server, or sends the data in UTF-8 encoding for conversion by the database server. db2.jcc.sendCharInputsUTF8 applies to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS database servers only. If this property is also set at the connection level, the connection-level setting overrides this value.

Valid values for the properties include the following values:

no, false, or 2

Specifies the default value that the IBM Data Server Driver for JDBC and SQLJ converts character input data to the target encoding before the data is sent to the Db2 for z/OS database server.

yes, true, or 1

Specifies that the IBM Data Server Driver for JDBC and SQLJ sends character input data to the Db2 for z/OS database server in UTF-8 encoding. The data source converts the data from UTF-8 encoding to the target CCSID.

Specify yes, true, or 1 only if conversion to the target CCSID by the SDK for Java causes character conversion problems. The most common problem occurs when you use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to insert a Unicode line feed character (U+000A) into a table column that has CCSID 37, and then retrieve that data from a non-z/OS client. If the SDK for Java does the conversion during insertion of the character into the column, the line feed character is converted to the EBCDIC new line character X'15'. However, during retrieval, some SDKs for Java on operating systems other than z/OS convert the X'15' character to the Unicode next line character (U+0085) instead of the line feed character (U+000A). The next line character causes unexpected behavior for some XML parsers. If you set db2.jcc.sendCharInputsUTF8 to yes, the Db2 for z/OS database server converts the U+000A character to the EBCDIC line feed character X'25' during insertion into the column, so the character is always retrieved as a line feed character.

Conversion of data to the target CCSID on the data source might cause the IBM Data Server Driver for JDBC and SQLJ to use more memory than conversion by the driver. The driver allocates memory for conversion of character data from the source encoding to the encoding of the data that it sends to the data source. The amount of space that the driver allocates for character data that is sent to a table column is based on the maximum length of the data. UTF-8 data can require up to 3 bytes for each character. Therefore, if the driver sends UTF-8 data to the data source, the driver needs to allocate three times the maximum number of characters in the input data. If the driver does the conversion, and the target CCSID is a single-byte CCSID, the driver needs to allocate only the maximum number of characters in the input data.

For example, any of the following settings for db2.jcc.sendCharInputsUTF8 causes the IBM Data Server Driver for JDBC and SQLJ to convert input character strings to UTF-8, rather than the target encoding, before sending the data to the data source:

```
db2.jcc.sendCharInputsUTF8=yes
db2.jcc.sendCharInputsUTF8=true
db2.jcc.sendCharInputsUTF8=1
```

This configuration property applies only to Db2 for z/OS.

db2.jcc.sqljStmtCacheSize

Specifies the maximum number of statements that are in the SQLJ statement cache for each `DefaultContext` instance and each JVM thread. This value applies to SQLJ stored procedures that run in a 64-bit, multi-threaded environment. The default is 10 statements.

In a multi-threaded environment, the IBM Data Server Driver for JDBC and SQLJ caches statements that are associated with each instance of a `DefaultContext` object that is used by each JVM thread. When the driver attempts to cache a statement after the db2.jcc.sqljStmtCacheSize value is reached. The least recently used cached statement is purged and replaced by the new statement.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 11 or later.

db2.jcc.sqljToolsExitJVMOnCompletion
Specifies whether the Java programs that underlie SQLJ tools such as db2sqljcustomize and db2sqljbind issue the `System.exit` call on return to the calling programs.

Possible values are:

true
Specifies that the Java programs that underlie SQLJ tools issue the `System.exit` call upon completion. `true` is the default.

false
Specifies that the Java programs that underlie SQLJ tools do not issue the `System.exit` call.

db2.jcc.sqljUncustomizedWarningOrException
Specifies the action that the IBM Data Server Driver for JDBC and SQLJ takes when an uncustomized SQLJ application runs. db2.jcc.sqljUncustomizedWarningOrException can have the following values:

0
The IBM Data Server Driver for JDBC and SQLJ does not throw a `Warning` or `Exception` when an uncustomized SQLJ application is run. The value 0 is the default.

1
The IBM Data Server Driver for JDBC and SQLJ throws a `Warning` when an uncustomized SQLJ application is run.

2
The IBM Data Server Driver for JDBC and SQLJ throws an `Exception` when an uncustomized SQLJ application is run.

This configuration property applies only to Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems.

db2.jcc.ssid
Specifies the Db2 for z/OS subsystem to which applications make connections with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

The db2.jcc.ssid value can be the name of the local Db2 subsystem or a group attachment name or subgroup attachment name.

The property is illustrated in the following example:

```
db2.jcc.ssid=DB2A
```

The ssid `Connection` and `DataSource` property overrides db2.jcc.ssid.

If you specify a group attachment name or subgroup attachment name, and the Db2 subsystem to which an application is connected fails, the connection ends. However, when new connections use that group attachment name or subgroup attachment name, Db2 for z/OS uses group attachment or subgroup attachment processing to find an active Db2 subsystem to which to connect.

If you do not specify the db2.jcc.ssid property, the IBM Data Server Driver for JDBC and SQLJ uses the SSID value from the application defaults load module. When you install Db2 for z/OS, an application defaults load module is created in the *prefix*.SDSNEXIT data set and the *prefix*.SDSNLOAD data set. Other application defaults load modules might be created in other data sets for selected applications.

The IBM Data Server Driver for JDBC and SQLJ must load an application defaults load module before it can read the SSID value. z/OS searches data sets in the following places, and in the following order, for the application defaults load module:

1. Job pack area (JPA)
2. TASKLIB
3. STEPLIB or JOBLIB
4. LPA
5. Libraries in the link list

You need to ensure that if your system has more than one copy of the application defaults load module, z/OS finds the data set that contains the correct copy for the IBM Data Server Driver for JDBC and SQLJ first.

This configuration property applies only to Db2 for z/OS.

db2.jcc.sslCertLocation or db2.jcc.override.sslCertLocation
Specifies that an application can configure the location of a trusted certificate file. For applications in possession of the database server certificate, sslCertLocation is the only property that is needed to be configured to instruct IBM Data Server Driver for JDBC and SQLJ to trust the certificate for SSL connections. This property removes the need to import the certificate into a Java truststore database and related driver configurations.

The default value for sslCertLocation is provided by the db2.jcc.sslCertLocation configuration property. If the db2.jcc.sslCertLocation configuration property is not specified, sslTruststoreLocation, and sslCertLocation properties are not configured, and sslConnection is set to `true`, IBM Data Server Driver for JDBC and SQLJ uses the default truststore for the Java runtime environment.

The db2.jcc.override.sslCertLocation property overrides the sslCertLocation property for a `Connection` or `DataSource` object.

db2.jcc.sslClientHostnameValidation or db2.jcc.override.sslClientHostnameValidation
Specifies whether the IBM Data Server Driver for JDBC and SQLJ performs client host name validation when establishing a connection to a data server that uses transport layer security (TLS). Host name validation is performed according to the standard that is specified in IETF RFC 6125.

sslClientHostnameValidation can have one of the following values:

BASIC
Specifies that host name validation is enabled. During the TLS handshake, when the data server sends its certificate to the driver, the driver checks whether the host name or its corresponding IP address in the certificate matches the host name or corresponding IP address that the application provides to the driver.

OFF
Specifies that host name validation is disabled. This is the default.

This property applies only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS and to Db2 on Linux, UNIX, and Windows systems .

The db2.jcc.override.sslClientHostnameValidation property overrides the sslClientHostnameValidation property for a `Connection` or `DataSource` object.

db2.jcc.sslConnection or db2.jcc.override.sslConnection
Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses an SSL socket to connect to the data source. If the value is `true`, the connection uses an SSL socket. If the value is `false`, the connection uses a plain socket.

The db2.jcc.override.sslConnection property overrides the sslConnection property for a `Connection` or `DataSource` object.

If no property is specified, the default value is `false`.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

db2.jcc.sslKeyStoreLocation or db2.jcc.override.sslKeyStoreLocation
Specifies the name of the Java keystore on the client that contains the client certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection property is set to `true`.

If db2.jcc.sslKeyStoreLocation or db2.jcc.override.sslKeyStoreLocation, or sslKeyStoreLocation is set, and db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection is set to `true`, the IBM Data Server Driver for JDBC and SQLJ uses the db2.jcc.sslKeyStoreLocation,

db2.jcc.override.sslKeyStoreLocation, or sslKeyStoreLocation value instead of the value in the javax.net.ssl.keyStore Java property.

The db2.jcc.override.sslKeyStoreLocationproperty overrides the sslKeyStoreLocation property for a `Connection` or `DataSource` object.

If no property is specified, the default value is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.This configuration property applies only to Db2 for z/OS.

db2.jcc.sslKeyStorePassword or db2.jcc.override.sslKeyStorePassword

Specifies the password for the Java keystore on the client that contains the client certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection property is set to `true`.

If db2.jcc.sslKeyStorePassword, db2.jcc.override.sslKeyStorePassword, or sslKeyStorePassword is set, and db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection is set to `true`, the IBM Data Server Driver for JDBC and SQLJ uses the db2.jcc.sslKeyStorePassword, db2.jcc.override.sslKeyStorePassword, or sslKeyStorePassword value instead of the value in the javax.net.ssl.keyStorePassword Java property.

The db2.jcc.override.sslKeyStorePasswordproperty overrides the sslKeyStorePassword property for a `Connection` or `DataSource` object.

If no property is specified, the default value is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.This configuration property applies only to Db2 for z/OS.

db2.jcc.sslKeyStoreType or db2.jcc.override.sslKeyStoreType

Specifies the type for the Java keystore on the client that contains the client certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection property is set to `true`.

If db2.jcc.sslKeyStoreType, db2.jcc.override.sslKeyStoreType, or sslKeyStoreType is set, and db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection is set to `true`, the IBM Data Server Driver for JDBC and SQLJ uses the db2.jcc.sslKeyStoreType, db2.jcc.override.sslKeyStoreType, or sslKeyStoreType value instead of the value in the javax.net.ssl.keyStoreType Java property.

The db2.jcc.override.sslKeyStoreTypeproperty overrides the sslKeyStoreType property for a `Connection` or `DataSource` object.

If no property is specified, the default value is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.This configuration property applies only to Db2 for z/OS.

db2.jcc.sslTrustStoreLocation or db2.jcc.override.sslTrustStoreLocation

Specifies the name of the Java truststore on the client that contains the server certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection property is set to `true`.

If db2.jcc.sslTrustStoreLocation or db2.jcc.override.sslTrustStoreLocation, or sslTrustStoreLocation is set, and db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection is set to `true`, the IBM Data Server Driver for JDBC and SQLJ uses the db2.jcc.sslTrustStoreLocation, db2.jcc.override.sslTrustStoreLocation, or sslTrustStoreLocation value instead of the value in the javax.net.ssl.trustStore Java property.

The db2.jcc.override.sslTrustStoreLocation property overrides the sslTrustStoreLocation property for a `Connection` or `DataSource` object.

If no property is specified, the default value is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

db2.jcc.sslTrustStorePassword or db2.jcc.override.sslTrustStorePassword
Specifies the password for the Java truststore on the client that contains the server certificate for an SSL connection.

The IBM Data Server Driver for JDBC and SQLJ uses this option only if the db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection property is set to `true`.

If db2.jcc.sslTrustStorePassword, db2.jcc.override.sslTrustStorePassword, or sslTrustStorePassword is set, and db2.jcc.sslConnection, db2.jcc.override.sslConnection, or sslConnection is set to `true`, the IBM Data Server Driver for JDBC and SQLJ uses the db2.jcc.sslTrustStorePassword, db2.jcc.override.sslTrustStorePassword, or sslTrustStorePassword value instead of the value in the javax.net.ssl.trustStorePassword Java property.

The db2.jcc.override.sslTrustStorePassword property overrides the sslTrustStorePassword property for a `Connection` or `DataSource` object.

If no property is specified, the default value is null.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

db2.jcc.traceDirectory or db2.jcc.override.traceDirectory
Enables the IBM Data Server Driver for JDBC and SQLJ trace for Java driver code, and specifies a directory into which trace information is written. These properties do not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. When db2.jcc.override.traceDirectory is specified, trace information for multiple connections on the same `DataSource` is written to multiple files.

When db2.jcc.override.traceDirectory is specified, a connection is traced to a file named *file-name_origin_n*.

- *n* is the *n*th connection for a `DataSource`.
- If neither db2.jcc.traceFileName nor db2.jcc.override.traceFileName is specified, *file-name* is traceFile. If db2.jcc.traceFileName or db2.jcc.override.traceFileName is also specified, *file-name* is the value of db2.jcc.traceFileName or db2.jcc.override.traceFileName.
- *origin* indicates the origin of the log writer that is in use. Possible values of *origin* are:

  cpds
  The log writer for a `DB2ConnectionPoolDataSource` object.

  driver
  The log writer for a `DB2Driver` object.

  global
  The log writer for a `DB2TraceManager` object.

  sds
  The log writer for a `DB2SimpleDataSource` object.

  xads
  The log writer for a `DB2XADataSource` object.

The db2.jcc.override.traceDirectory property overrides the `traceDirectory` property for a `Connection` or `DataSource` object.

For example, specifying the following setting for db2.jcc.override.traceDirectory enables tracing of the IBM Data Server Driver for JDBC and SQLJ Java code to files in a directory named /SYSTEM/tmp:

```
db2.jcc.override.traceDirectory=/SYSTEM/tmp
```

You must set the trace properties under the direction of IBM Software Support.

db2.jcc.traceLevel or db2.jcc.override.traceLevel
Specifies what to trace.

The db2.jcc.override.traceLevel property overrides the `traceLevel` property for a `Connection` or `DataSource` object.

You specify one or more trace levels by specifying a decimal value. The trace levels are the same as the trace levels that are defined for the traceLevel property on a `Connection` or `DataSource` object.

To specify more than one trace level, do an OR (|) operation on the values, and specify the result in decimal in the db2.jcc.traceLevel or db2.jcc.override.traceLevel specification.

For example, suppose that you want to specify TRACE_DRDA_FLOWS and TRACE_CONNECTIONS for db2.jcc.override.traceLevel. TRACE_DRDA_FLOWS has a hexadecimal value of X'40'. TRACE_CONNECTION_CALLS has a hexadecimal value of X'01'. To specify both traces, do a bitwise OR operation on the two values, which results in X'41'. The decimal equivalent is 65, so you specify:

```
db2.jcc.override.traceLevel=65
```

db2.jcc.traceFile or db2.jcc.override.traceFile
Enables the IBM Data Server Driver for JDBC and SQLJ trace for Java driver code, and specifies the name on which the trace file names are based.The db2.jcc.traceFile property does not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Specify a fully qualified z/OS UNIX System Services file name for the db2.jcc.override.traceFile property value.

The db2.jcc.override.traceFile property overrides the `traceFile` property for a `Connection` or `DataSource` object.

For example, specifying the following setting for db2.jcc.override.traceFile enables tracing of the IBM Data Server Driver for JDBC and SQLJ Java code to a file named `/SYSTEM/tmp/jdbctrace`:

```
db2.jcc.override.traceFile=/SYSTEM/tmp/jdbctrace
```

You must set the trace properties under the direction of IBM Support.

db2.jcc.traceFileAppend or db2.jcc.override.traceFileAppend
Specifies whether to append to or overwrite the file that is specified by the db2.jcc.override.traceFile property. These properties do not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS. Valid values are `true` or `false`. The default is `false`, which means that the file that is specified by the traceFile property is overwritten.

The db2.jcc.override.traceFileAppend property overrides the `traceFileAppend` property for a `Connection` or `DataSource` object.

For example, specifying the following setting for db2.jcc.override.traceFileAppend causes trace data to be added to the existing trace file:

```
db2.jcc.override.traceFileAppend=true
```

You must set the trace properties under the direction of IBM Support.

db2.jcc.traceFileCount
Specifies the maximum number of trace files for circular tracing. The IBM Data Server Driver for JDBC and SQLJ uses this property only when db2.jcc.traceOption is set to 1. The default value is 2.

You must set the trace properties under the direction of IBM Support.

db2.jcc.traceFileSize
Specifies the maximum size of each trace file, for circular tracing. The IBM Data Server Driver for JDBC and SQLJ uses this property only when db2.jcc.traceOption is set to 1. The default value is 10485760 (10 MB).

You must set the trace properties under the direction of IBM Support.

db2.jcc.traceOption

Specifies how trace data is collected. The data type of this property is int. Possible values of the property include the following values:

0

Specifies the default value that means a single trace file is generated, and that no limit to the size of the file exist.

1

Specifies that the IBM Data Server Driver for JDBC and SQLJ does circular tracing. Circular tracing is done as follows:

1. When an application writes its first trace record, the driver creates a file.
2. The driver writes trace data to the file.
3. When the size of the file is equal to the value of property db2.jcc.traceFileSize, the driver creates another file.
4. The driver repeats steps "2" on page 316 and "3" on page 316 until the number of files to which data written is equal to the value of property db2.jcc.traceFileCount.
5. The driver writes data to the first trace file, overwriting the existing data.
6. The driver repeats steps "3" on page 316 through "5" on page 316 until the application completes.

The file names for the trace files are the file names that are determined by the db2.jcc.traceFile, db2.jcc.override.traceFile, db2.jcc.traceDirectory, db2.jcc.override.traceDirectory property, which is appended with .1 for the first file, .2 for the second file, and so on.

You must set the trace properties under the direction of IBM Support.

db2.jcc.tracePolling

Indicates whether the IBM Data Server Driver for JDBC and SQLJ polls the global configuration file for changes in trace directives and modifies the trace behavior to match the new trace directives. Possible values are true or false. The default is false for version 3.69 or earlier of the IBM Data Server Driver for JDBC and SQLJ, and the default is true for versions 3.69 and 4.19 or later of the IBM Data Server Driver for JDBC and SQLJ.

The IBM Data Server Driver for JDBC and SQLJ modifies the trace behavior at the beginning of the next polling interval after the configuration properties file is changed. If db2.jcc.tracePolling is set to `true` while an application is running, the trace is enabled, and information about all the `PreparedStatement` objects that were created by the application before the trace was enabled are dumped to the trace destination.

db2.jcc.tracePolling polls the following global configuration properties:

- db2.jcc.override.traceLevel
- db2.jcc.override.traceFile
- db2.jcc.override.traceDirectory
- db2.jcc.override.traceFileAppend
- db2.jcc.t2zosTraceFile
- db2.jcc.t2zosTraceBufferSize
- db2.jcc.t2zosTraceWrap

db2.jcc.tracePollingInterval

Specifies the interval, in seconds, for polling the IBM Data Server Driver for JDBC and SQLJ global configuration file for changes in trace directives. The property value is a positive integer. The default is 60. For the specified trace polling interval to be used, the db2.jcc.tracePollingInterval property must be set *before* the driver is loaded and initialized. Changes to db2.jcc.tracePollingInterval after the driver is loaded and initialized have no effect.

db2.jcc.t2zosTraceFile

Enables the IBM Data Server Driver for JDBC and SQLJ trace for C/C++ native driver code for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, and specifies the name on which the trace file names are based. This property is required for collecting trace data for C/C++ native driver code.

Specify a fully qualified z/OS UNIX System Services file name for the db2.jcct.t2zosTraceFile property value.

For example, specifying the following setting for db2.jcct.t2zosTraceFile enables tracing of the IBM Data Server Driver for JDBC and SQLJ C/C++ native code to a file named /SYSTEM/tmp/jdbctraceNative:

```
db2.jcc.t2zosTraceFile=/SYSTEM/tmp/jdbctraceNative
```

You should set the trace properties under the direction of IBM Support.

This configuration property applies only to Db2 for z/OS.

db2.jcc.t2zosTraceBufferSize

Specifies the size, in KB, of a trace buffer in virtual storage that is used for tracing the processing that is done by the C/C++ native driver code. This value is also the maximum amount of C/C++ native driver trace information that can be collected.

Specify an integer between 64 (64 KB) and 4096 (4096 KB). The default is 256 (256 KB).

The JDBC driver determines the trace buffer size as shown in the following table:

Specified value (*n*)	**Trace buffer size (KB)**
<64	64
64<=*n*<128	64
128<=*n*<256	128
256<=*n*<512	256
512<=*n*<1024	512
1024<=*n*<2048	1024
2048<=*n*<4096	2048
n>=4096	4096

db2.jcc.t2zosTraceBufferSize is used only if the db2.jcc.t2zosTraceFile property is set.

Recommendation: To avoid a performance impact, specify a value of 1024 or less.

For example, to set a trace buffer size of 1024 KB, use this setting:

```
db2.jcc.t2zosTraceBufferSize=1024
```

You must set the trace properties under the direction of IBM Support.

This configuration property applies only to Db2 for z/OS.

db2.jcc.t2zosTraceWrap

Enables or disables wrapping of the SQLJ trace. db2.jcc.t2zosTraceWrap can have one of the following values:

1
Wrap the trace.

0
Do not wrap the trace.

The default is 1. This parameter is optional. The following example shows how to set the property:

```
DB2SQLJ_TRACE_WRAP=0
```

You must set db2.jcc.t2zosTraceWrap only under the direction of IBM Support.

This configuration property applies only to Db2 for z/OS.

db2.jcc.useCcsid420ShapedConverter
Specifies whether Arabic character data that is in EBCDIC CCSID 420 maps to Cp420S encoding.

db2.jcc.useCcsid420ShapedConverter applies only to connections to Db2 for z/OS database servers.

If the value of db2.jcc.useCcsid420ShapedConverter is `true`, CCSID 420 maps to Cp420S encoding. If the value of db2.jcc.useCcsid420ShapedConverter is `false`, CCSID 420 maps to Cp420 encoding. The value `false` is the default.

This configuration property applies only to Db2 for z/OS.

db2.jcc.useClientSideLicenseFirst or db2.jcc.override.useClientSideLicenseFirst
Specifies whether the IBM Data Server Driver for JDBC and SQLJ checks the client-side license before the server-side license for permission to access the data server.

useClientSideLicenseFirst can have one of the following values:

1
Check whether a client-side license exists, and if so, use it to validate the connection. If a client-side license does not exist, check for a server-side license. If neither license exists, the driver throws a LicenseException.

2 or 0
Check whether a server-side license exists, and if so, use it to validate the connection. If a server-side license does not exist, check for a client-side license. If neither license exists, the driver throws a LicenseException. This is the default behavior.

db2.jcc.useClientSideLicenseFirst applies to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS, Db2 for IBM i, and Db2 on Cloud, and to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Related concepts
Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties
The IBM Data Server Driver for JDBC and SQLJ configuration properties let you set property values that have driver-wide scope. Those settings apply across applications and `DataSource` instances. You can change the settings without having to change application source code or `DataSource` characteristics.

Driver support for JDBC APIs

The JDBC drivers that are supported by Db2 and IBM Informix database systems have different levels of support for JDBC methods.

The following tables list the JDBC interfaces and indicate which drivers supports them. The drivers and their supported platforms are:

Table 44. JDBC drivers for Db2 and IBM Informix database systems

JDBC driver name	Associated data source
IBM Data Server Driver for JDBC and SQLJ	Db2 on Linux, UNIX, and Windows systems, Db2 for z/OS, or IBM Informix
IBM Informix JDBC Driver (IBM Informix JDBC Driver)	IBM Informix

If a method has JDBC 2.0 and JDBC 3.0 forms, the IBM Data Server Driver for JDBC and SQLJ supports all forms. The Db2 JDBC Type 2 Driver for Linux, UNIX and Windows supports only the JDBC 2.0 forms.

Table 45. Support for java.sql.Array methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ "1" on page 319 support	IBM Informix JDBC Driver support
free "2" on page 319	Yes	Yes
getArray	Yes	Yes
getBaseType	Yes	Yes
getBaseTypeName	Yes	Yes
getResultSet	Yes	Yes

Notes:

1. Under the IBM Data Server Driver for JDBC and SQLJ, `Array` methods are supported for connections to Db2 on Linux, UNIX, and Windows systems data sources only.
2. This is a JDBC 4.0 method.

Table 46. Support for java.sql.BatchUpdateException methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes
getUpdateCounts	Yes	Yes

Table 47. Support for java.sql.Blob methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
free "1" on page 319	Yes	Yes
getBinaryStream	Yes "2" on page 319	Yes
getBytes	Yes	Yes
length	Yes	Yes
position	Yes	Yes
setBinaryStream "3" on page 319	Yes	Yes
setBytes "3" on page 319	Yes	Yes
truncate "3" on page 319	Yes	Yes

Notes:

1. This is a JDBC 4.0 method.
2. Supported forms of this method include the following JDBC 4.0 form:

```
getBinaryStream(long pos, long length)
```

3. For versions of the IBM Data Server Driver for JDBC and SQLJ before version 3.50, these methods cannot be used if a `Blob` is passed to a stored procedure as an IN or INOUT parameter, and the methods are used on the `Blob` in the stored procedure.

Table 48. Support for java.sql.CallableStatement methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.sql.Statement	Yes	Yes
Methods inherited from java.sql.PreparedStatement	Yes"1" on page 321	Yes
getArray	No	Yes
getBigDecimal	Yes"3" on page 321	Yes
getBlob	Yes"3" on page 321	Yes
getBoolean	Yes"3" on page 321	Yes
getByte	Yes"3" on page 321	Yes
getBytes	Yes"3" on page 321	Yes
getClob	Yes"3" on page 321	Yes
getDate	Yes"3" on page 321,"5" on page 321	Yes
getDouble	Yes"3" on page 321	Yes
getFloat	Yes"3" on page 321	Yes
getInt	Yes"3" on page 321	Yes
getLong	Yes"3" on page 321	Yes
getObject	Yes"3" on page 321,"4" on page 321, "6" on page 321	Yes
getRef	No	No
getRowId"2" on page 321	Yes	No
getShort	Yes"3" on page 321	Yes
getString	Yes"3" on page 321	Yes
getTime	Yes"3" on page 321,"5" on page 321	Yes
getTimestamp	Yes"3" on page 321,"5" on page 321	Yes
getURL	Yes	No
registerOutParameter	Yes"7" on page 321	Yes"7" on page 321
setAsciiStream	Yes"8" on page 321	Yes
setBigDecimal	Yes"8" on page 321	Yes
setBinaryStream	Yes"8" on page 321	Yes
setBoolean	Yes"8" on page 321	Yes
setByte	Yes"8" on page 321	Yes
setBytes	Yes"8" on page 321	Yes
setCharacterStream	Yes"8" on page 321	Yes
setDate	Yes"8" on page 321	Yes
setDouble	Yes"8" on page 321	Yes

Table 48. Support for java.sql.CallableStatement methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
setFloat	Yes"8" on page 321	Yes
setInt	Yes"8" on page 321	Yes
setLong	Yes"8" on page 321	Yes
setNull	Yes"8" on page 321,,"9" on page 321	Yes
setObject	Yes"8" on page 321,	Yes
setShort	Yes"8" on page 321	Yes
setString	Yes"8" on page 321	Yes
setTime	Yes"8" on page 321	Yes
setTimestamp	Yes"8" on page 321	Yes
setURL	Yes	No
wasNull	Yes	Yes

Notes:

1. The inherited `getParameterMetaData` method is not supported if the data source is Db2 for z/OS.
2. This is a JDBC 4.0 method.
3. The following forms of `CallableStatement.getXXX` methods are not supported if the data source is Db2 for z/OS:

   ```
   getXXX(String parameterName)
   ```

4. The following JDBC 4.1 method is supported:

   ```
   getObject(int parameterIndex, java.lang.Class<T> type)
   getObject(java.lang.String parameterName, java.lang.Class<T> type)
   ```

5. The database server does no timezone adjustment for datetime values. The JDBC driver adjusts a value for the local timezone after retrieving the value from the server if you specify a form of the getDate, getTime, or getTimestamp method that includes a java.util.Calendar parameter.
6. The following form of the `getObject` method is not supported:

   ```
   getObject(int parameterIndex, java.util.Map  map)
   ```

7. The following form of the `registerOutParameter` method is not supported:

   ```
   registerOutParameter(int parameterIndex, int jdbcType, String typeName)
   ```

8. The following forms of `CallableStatement.setXXX` methods are not supported if the data source is Db2 for z/OS:

   ```
   setXXX(String parameterName,…)
   ```

9. The following form of `setNull` is not supported:

   ```
   setNull(int parameterIndex, int jdbcType, String typeName)
   ```

Table 49. Support for java.sql.Clob methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
free"1" on page 322	Yes	Yes
getAsciiStream	Yes	Yes
getCharacterStream	Yes"2" on page 322	Yes
getSubString	Yes	Yes
length	Yes	Yes
position	Yes	Yes
setAsciiStream"3" on page 322	Yes	Yes
setCharacterStream"3" on page 322	Yes	Yes
setString"3" on page 322	Yes	Yes
truncate"3" on page 322	Yes	Yes

Notes:

1. This is a JDBC 4.0 method.
2. Supported forms of this method include the following JDBC 4.0 form:

```
getCharacterStream(long pos, long length)
```

3. For versions of the IBM Data Server Driver for JDBC and SQLJ before version 3.50, these methods cannot be used if a `Clob` is passed to a stored procedure as an IN or INOUT parameter, and the methods are used on the `Clob` in the stored procedure.

Table 50. Support for javax.sql.CommonDataSource methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getLoginTimeout	Yes	Yes
getLogWriter	Yes	Yes
getParentLogger"1" on page 322	Yes	No
setLoginTimeout	Yes	Yes
setLogWriter	Yes	Yes

Notes:

1. This is a JDBC 4.1 method.

Table 51. Support for java.sql.Connection methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
abort"1" on page 324	Yes	No
clearWarnings	Yes	Yes
close	Yes	Yes
commit	Yes	Yes

Table 51. Support for java.sql.Connection methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
createBlob"2" on page 324	Yes	Yes
createClob"2" on page 324	Yes	Yes
createStatement	Yes	Yes
getAutoCommit	Yes	Yes
getCatalog	Yes	Yes
getClientInfo"2" on page 324	Yes	Yes
getHoldability	Yes	Yes
getMetaData	Yes	Yes
getNetworkTimeout"1" on page 324	Yes	No
getSchema"1" on page 324	Yes	No
getTransactionIsolation	Yes	Yes
getTypeMap	No	Yes
getWarnings	Yes	Yes
isClosed	Yes	Yes
isReadOnly	Yes	Yes
isValid"2" on page 324,"3" on page 324	Yes	Yes
nativeSQL	Yes	Yes
prepareCall	Yes"4" on page 324	Yes
prepareStatement	Yes	Yes
releaseSavepoint	Yes	Yes
rollback	Yes	Yes
setAutoCommit	Yes	Yes
setCatalog	Yes	No
setClientInfo"2" on page 324	Yes	No
setNetworkTimeout"1" on page 324	Yes	No
setReadOnly	Yes"5" on page 324	No
setSavepoint	Yes	Yes
setSchema"1" on page 324	Yes	No
setTransactionIsolation	Yes	Yes
setTypeMap	No	Yes

Table 51. Support for java.sql.Connection methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support

Notes:

1. This is a JDBC 4.1 method.
2. This is a JDBC 4.0 method.
3. Under IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, an `SQLException` is thrown if the *timeout* parameter value is less than 0. Under IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, an `SQLException` is thrown if the if the *timeout* parameter value is not 0.
4. If the stored procedure in the CALL statement is on Db2 for z/OS, the parameters of the CALL statement cannot be expressions.
5. The driver does not use the setting. For the IBM Data Server Driver for JDBC and SQLJ, a connection can be set as read-only through the `readOnly` property for a `Connection` or `DataSource` object.

Table 52. Support for javax.sql.ConnectionEvent methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.util.EventObject	Yes	Yes
getSQLException	Yes	Yes

Table 53. Support for javax.sql.ConnectionEventListener methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
connectionClosed	Yes	Yes
connectionErrorOccurred	Yes	Yes

Table 54. Support for javax.sql.ConnectionPoolDataSource methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getLoginTimeout	Yes	Yes
getLogWriter	Yes	Yes
getPooledConnection	Yes	Yes
setLoginTimeout	Yes[“1” on page 324]	Yes
setLogWriter	Yes	Yes

Note:

1. This method is not supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Table 55. Support for java.sql.DatabaseMetaData methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
allProceduresAreCallable	Yes	Yes
allTablesAreSelectable	Yes"1" on page 330	Yes"1" on page 330
dataDefinitionCausesTransactionCommit	Yes	Yes
dataDefinitionIgnoredInTransactions	Yes	Yes
deletesAreDetected	Yes	Yes
doesMaxRowSizeIncludeBlobs	Yes	Yes
generatedKeyAlwaysReturned"2" on page 330	Yes	Yes
getAttributes	Yes"3" on page 330	Yes
getBestRowIdentifier	Yes	Yes
getCatalogs	Yes	Yes
getCatalogSeparator	Yes	Yes
getCatalogTerm	Yes	Yes
getClientInfoProperties[7]	Yes	No
getColumnPrivileges	Yes	Yes
getColumns	Yes"8" on page 330	Yes"11" on page 330
getConnection	Yes	Yes
getCrossReference	Yes	Yes
getDatabaseMajorVersion	Yes	Yes
getDatabaseMinorVersion	Yes	Yes
getDatabaseProductName	Yes	Yes
getDatabaseProductVersion	Yes	Yes
getDefaultTransactionIsolation	Yes	Yes
getDriverMajorVersion	Yes	Yes
getDriverMinorVersion	Yes	Yes
getDriverName	Yes"9" on page 330	Yes
getDriverVersion	Yes	Yes
getExportedKeys	Yes	Yes
getFunctionColumns"7" on page 330	Yes	Yes
getFunctions"7" on page 330	Yes	Yes
getExtraNameCharacters	Yes	Yes
getIdentifierQuoteString	Yes	Yes
getImportedKeys	Yes	Yes

Table 55. Support for java.sql.DatabaseMetaData methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getIndexInfo	Yes	Yes
getJDBCMajorVersion	Yes	Yes
getJDBCMinorVersion	Yes	Yes
getMaxBinaryLiteralLength	Yes	Yes
getMaxCatalogNameLength	Yes	Yes
getMaxCharLiteralLength	Yes	Yes
getMaxColumnNameLength	Yes	Yes
getMaxColumnsInGroupBy	Yes	Yes
getMaxColumnsInIndex	Yes	Yes
getMaxColumnsInOrderBy	Yes	Yes
getMaxColumnsInSelect	Yes	Yes
getMaxColumnsInTable	Yes	Yes
getMaxConnections	Yes	Yes
getMaxCursorNameLength	Yes	Yes
getMaxIndexLength	Yes	Yes
getMaxProcedureNameLength	Yes	Yes
getMaxRowSize	Yes	Yes
getMaxSchemaNameLength	Yes	Yes
getMaxStatementLength	Yes	Yes
getMaxStatements	Yes	Yes
getMaxTableNameLength	Yes	Yes
getMaxTablesInSelect	Yes	Yes
getMaxUserNameLength	Yes	Yes
getNumericFunctions	Yes	Yes
getPrimaryKeys	Yes	Yes
getProcedureColumns	Yes"8" on page 330	Yes
getProcedures	Yes"8" on page 330	Yes
getProcedureTerm	Yes	Yes
getPseudoColumns"2" on page 330	Yes	No
getResultSetHoldability	Yes	Yes
getRowIdLifetime"7" on page 330	Yes	No

Table 55. Support for java.sql.DatabaseMetaData methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getSchemas	Yes"10" on page 330	Yes"11" on page 330
getSchemaTerm	Yes	Yes
getSearchStringEscape	Yes	Yes
getSQLKeywords	Yes	Yes
getSQLStateType	Yes	Yes
getStringFunctions	Yes	Yes
getSuperTables	Yes"3" on page 330	Yes
getSuperTypes	Yes"3" on page 330	Yes
getSystemFunctions	Yes	Yes
getTablePrivileges	Yes	Yes
getTables	Yes	Yes"11" on page 330
getTableTypes	Yes	Yes
getTimeDateFunctions	Yes	Yes
getTypeInfo	Yes	Yes
getUDTs	No	Yes"12" on page 330
getURL	Yes	Yes
getUserName	Yes	Yes
getVersionColumns	Yes	Yes
insertsAreDetected	Yes	Yes
isCatalogAtStart	Yes	Yes
isReadOnly	Yes	Yes
locatorsUpdateCopy	Yes"4" on page 330	Yes"4" on page 330
nullPlusNonNullIsNull	Yes	Yes
nullsAreSortedAtEnd	Yes"5" on page 330	Yes"5" on page 330
nullsAreSortedAtStart	Yes	Yes
nullsAreSortedHigh	Yes"6" on page 330	Yes"6" on page 330
nullsAreSortedLow	Yes"1" on page 330	Yes"1" on page 330
othersDeletesAreVisible	Yes	Yes
othersInsertsAreVisible	Yes	Yes
othersUpdatesAreVisible	Yes	Yes

Table 55. Support for java.sql.DatabaseMetaData methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
ownDeletesAreVisible	Yes	Yes
ownInsertsAreVisible	Yes	Yes
ownUpdatesAreVisible	Yes	Yes
storesLowerCaseIdentifiers	Yes"1" on page 330	Yes"1" on page 330
storesLowerCaseQuotedIdentifiers	Yes"5" on page 330	Yes"5" on page 330
storesMixedCaseIdentifiers	Yes	Yes
storesMixedCaseQuotedIdentifiers	Yes	Yes
storesUpperCaseIdentifiers	Yes"6" on page 330	Yes"6" on page 330
storesUpperCaseQuotedIdentifiers	Yes	Yes
supportsAlterTableWithAddColumn	Yes	Yes
supportsAlterTableWithDropColumn	Yes"1" on page 330	Yes"1" on page 330
supportsANSI92EntryLevelSQL	Yes	Yes
supportsANSI92FullSQL	Yes	Yes
supportsANSI92IntermediateSQL	Yes	Yes
supportsBatchUpdates	Yes	Yes
supportsCatalogsInDataManipulation	Yes"1" on page 330	Yes"1" on page 330
supportsCatalogsInIndexDefinitions	Yes	Yes
supportsCatalogsInPrivilegeDefinitions	Yes	Yes
supportsCatalogsInProcedureCalls	Yes"1" on page 330	Yes"1" on page 330
supportsCatalogsInTableDefinitions	Yes	Yes
SupportsColumnAliasing	Yes	Yes
supportsConvert	Yes	Yes
supportsCoreSQLGrammar	Yes	Yes
supportsCorrelatedSubqueries	Yes	Yes
supportsDataDefinitionAndDataManipulationTransactions	Yes	Yes
supportsDataManipulationTransactionsOnly	Yes	Yes
supportsDifferentTableCorrelationNames	Yes"5" on page 330	Yes"5" on page 330
supportsExpressionsInOrderBy	Yes	Yes
supportsExtendedSQLGrammar	Yes	Yes
supportsFullOuterJoins	Yes"4" on page 330	Yes"4" on page 330
supportsGetGeneratedKeys	Yes	Yes
supportsGroupBy	Yes	Yes

Table 55. Support for java.sql.DatabaseMetaData methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
supportsGroupByBeyondSelect	Yes	Yes
supportsGroupByUnrelated	Yes	Yes
supportsIntegrityEnhancementFacility	Yes	Yes
supportsLikeEscapeClause	Yes	Yes
supportsLimitedOuterJoins	Yes	Yes
supportsMinimumSQLGrammar	Yes	Yes
supportsMixedCaseIdentifiers	Yes	Yes
supportsMixedCaseQuotedIdentifiers	Yes"4" on page 330	Yes"4" on page 330
supportsMultipleOpenResults	Yes"6" on page 330	Yes"6" on page 330
supportsMultipleResultSets	Yes"6" on page 330	Yes"6" on page 330
supportsMultipleTransactions	Yes	Yes
supportsNamedParameters	Yes	Yes
supportsNonNullableColumns	Yes	Yes
supportsOpenCursorsAcrossCommit	Yes"4" on page 330	Yes"4" on page 330
supportsOpenCursorsAcrossRollback	Yes	Yes
supportsOpenStatementsAcrossCommit	Yes"4" on page 330	Yes"4" on page 330
supportsOpenStatementsAcrossRollback	Yes"4" on page 330	Yes"4" on page 330
supportsOrderByUnrelated	Yes	Yes
supportsOuterJoins	Yes	Yes
supportsPositionedDelete	Yes	Yes
supportsPositionedUpdate	Yes	Yes
supportsResultSetConcurrency	Yes	Yes
supportsResultSetHoldability	Yes	Yes
supportsResultSetType	Yes	Yes
supportsSavepoints	Yes	Yes
supportsSchemasInDataManipulation	Yes	Yes
supportsSchemasInIndexDefinitions	Yes	Yes
supportsSchemasInPrivilegeDefinitions	Yes	Yes
supportsSchemasInProcedureCalls	Yes	Yes
supportsSchemasInTableDefinitions	Yes	Yes
supportsSelectForUpdate	Yes	Yes
supportsStoredProcedures	Yes	Yes

Table 55. Support for java.sql.DatabaseMetaData methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
supportsSubqueriesInComparisons	Yes	Yes
supportsSubqueriesInExists	Yes	Yes
supportsSubqueriesInIns	Yes	Yes
supportsSubqueriesInQuantifieds	Yes	Yes
supportsSuperTables	Yes	No
supportsSuperTypes	Yes	No
supportsTableCorrelationNames	Yes	Yes
supportsTransactionIsolationLevel	Yes	Yes
supportsTransactions	Yes	Yes
supportsUnion	Yes	Yes
supportsUnionAll	Yes	Yes
updatesAreDetected	Yes	Yes
usesLocalFilePerTable	Yes	Yes
usesLocalFiles	Yes	Yes

Notes:

1. Db2 data sources return `false` for this method. IBM Informix data sources return `true`.
2. This is a JDBC 4.1 method.
3. This method is supported for connections to Db2 on Linux, UNIX, and Windows systems and IBM Informix only.
4. Under the IBM Data Server Driver for JDBC and SQLJ, Db2 data sources and IBM Informix data sources return `true` for this method. Under the IBM Informix JDBC Driver, IBM Informix data sources return `false`.
5. Under the IBM Data Server Driver for JDBC and SQLJ, Db2 data sources and IBM Informix data sources return `false` for this method. Under the IBM Informix JDBC Driver, IBM Informix data sources return `true`.
6. Db2 data sources return `true` for this method. IBM Informix data sources return `false`.
7. This is a JDBC 4.0 method.
8. This method returns the additional column that is described by the JDBC 4.0 specification.
9. JDBC 3.0 and earlier implementations of the IBM Data Server Driver for JDBC and SQLJ return "IBM DB2 JDBC Universal Driver Architecture."

   The JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ returns "IBM Data Server Driver for JDBC and SQLJ."
10. The JDBC 4.0 form and previous forms of this method are supported.
11. The Db2 JDBC Type 2 Driver for Linux, UNIX and Windows does not support the JDBC 3.0 form of this method.
12. The method can be executed, but it returns an empty `ResultSet`.

Table 56. Support for java.sql.DataSource methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getConnection	Yes	Yes
getLoginTimeout	Yes	Yes
getLogWriter	Yes	Yes
setLoginTimeout	Yes"1" on page 331	Yes
setLogWriter	Yes	Yes

Notes:

1. This method is not supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Table 57. Support for java.sql.DataTruncation methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Throwable	Yes	Yes
Methods inherited from java.sql.SQLException	Yes	Yes
Methods inherited from java.sql.SQLWarning	Yes	Yes
getDataSize	Yes	Yes
getIndex	Yes	Yes
getParameter	Yes	Yes
getRead	Yes	Yes
getTransferSize	Yes	Yes

Table 58. Support for java.sql.Driver methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
acceptsURL	Yes	Yes
connect	Yes	Yes
getMajorVersion	Yes	Yes
getMinorVersion	Yes	Yes
getParentLogger	Yes	No
getPropertyInfo	Yes	Yes
jdbcCompliant	Yes	Yes

Table 59. Support for java.sql.DriverManager methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
deregisterDriver	Yes	Yes

Table 59. Support for java.sql.DriverManager methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getConnection	Yes	Yes
getDriver	Yes	Yes
getDrivers	Yes	Yes
getLoginTimeout	Yes	Yes
getLogStream	Yes	Yes
getLogWriter	Yes	Yes
println	Yes	Yes
registerDriver	Yes	Yes
setLoginTimeout	Yes"1" on page 332	Yes
setLogStream	Yes	Yes
setLogWriter	Yes	Yes

Notes:

1. This method is not supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

Table 60. Support for java.sql.ParameterMetaData methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getParameterClassName	No	Yes
getParameterCount	Yes	Yes
getParameterMode	Yes	Yes
getParameterType	Yes	Yes
getParameterTypeName	Yes	Yes
getPrecision	Yes	Yes
getScale	Yes	Yes
isNullable	Yes	Yes
isSigned	Yes	Yes

Table 61. Support for javax.sql.PooledConnection methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
addConnectionEventListener	Yes	Yes
addStatementEventListener"1" on page 333	Yes	No
close	Yes	Yes
getConnection	Yes	Yes

Table 61. Support for javax.sql.PooledConnection methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
removeConnectionEventListener	Yes	Yes
removeStatementEventListener"1" on page 333	Yes	No

Notes:

1. This is a JDBC 4.0 method.

Table 62. Support for java.sql.PreparedStatement methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.sql.Statement	Yes	Yes
addBatch	Yes	Yes
clearParameters	Yes	Yes
execute	Yes	Yes
executeQuery	Yes	Yes
executeUpdate	Yes	Yes
getMetaData	Yes	Yes
getParameterMetaData	Yes	Yes
setArray	No	Yes
setAsciiStream	Yes"1" on page 335,"2" on page 335	Yes
setBigDecimal	Yes	Yes
setBinaryStream	Yes"1" on page 335,"3" on page 335	Yes
setBlob	Yes"4" on page 335	Yes
setBoolean	Yes	Yes
setByte	Yes	Yes
setBytes	Yes	Yes
setCharacterStream	Yes"1" on page 335,"5" on page 335	Yes
setClob	Yes"6" on page 335	Yes
setDate	Yes"8" on page 335	Yes"8" on page 335
setDouble	Yes	Yes
setFloat	Yes	Yes
setInt	Yes	Yes
setLong	Yes	Yes
setNClob	Yes"9" on page 335	Yes
setNString	Yes"10" on page 335	Yes
setNull	Yes"11" on page 335	Yes"11" on page 335

Table 62. Support for java.sql.PreparedStatement methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
setObject	Yes	Yes
setRef	No	No
setRowId"7" on page 335	Yes	No
setShort	Yes	Yes
setString	Yes"12" on page 335	Yes"12" on page 335
setTime	Yes"8" on page 335	Yes"8" on page 335
setTimestamp	Yes"8" on page 335	Yes"8" on page 335
setUnicodeStream	Yes	Yes
setURL	Yes	Yes

Table 62. Support for java.sql.PreparedStatement methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support

Notes:

1. If the value of the *length* parameter is -1, all of the data from the `InputStream` or `Reader` is read and sent to the data source.
2. Supported forms of this method include the following JDBC 4.0 forms:

```
setAsciiStream(int parameterIndex, InputStream x, long length)
setAsciiStream(int parameterIndex, InputStream x)
```

3. Supported forms of this method include the following JDBC 4.0 forms:

```
setBinaryStream(int parameterIndex, InputStream x, long length)
setBinaryStream(int parameterIndex, InputStream x)
```

4. Supported forms of this method include the following JDBC 4.0 form:

```
setBlob(int parameterIndex, InputStream inputStream, long length)
```

5. Supported forms of this method include the following JDBC 4.0 forms:

```
setCharacterStream(int parameterIndex, Reader reader, long length)
setCharacterStream(int parameterIndex, Reader reader)
```

6. Supported forms of this method include the following JDBC 4.0 form:

```
setClob(int parameterIndex, Reader reader, long length)
```

7. This is a JDBC 4.0 method.
8. The database server does no timezone adjustment for datetime values. The JDBC driver adjusts a value for the local timezone before sending the value to the server if you specify a form of the setDate, setTime, or setTimestamp method that includes a java.util.Calendar parameter.
9. Supported forms of this method include the following JDBC 4.0 form:

```
setNClob(int parameterIndex, Reader reader, long length)
```

10. setNString is not supported if the column has the FOR BIT DATA attribute or the data type is a binary data type.
11. The following form of `setNull` is not supported:

```
setNull(int parameterIndex, int jdbcType, String typeName)
```

12. setString is not supported if the column has the FOR BIT DATA attribute or the data type is a binary data type.

Table 63. Support for java.sql.Ref methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
get BaseTypeName	No	No

Table 64. Support for java.sql.ResultSet methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
absolute	Yes	Yes

Table 64. Support for java.sql.ResultSet methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
afterLast	Yes	Yes
beforeFirst	Yes	Yes
cancelRowUpdates	Yes	Yes
clearWarnings	Yes	Yes
close	Yes	Yes
deleteRow	Yes	Yes
findColumn	Yes	Yes
first	Yes	Yes
getArray	No	Yes
getAsciiStream	Yes	Yes
getBigDecimal	Yes	Yes
getBinaryStream	Yes"1" on page 339	Yes
getBlob	Yes	Yes
getBoolean	Yes	Yes
getByte	Yes	Yes
getBytes	Yes	Yes
getCharacterStream	Yes	Yes
getClob	Yes	Yes
getConcurrency	Yes	Yes
getCursorName	Yes	Yes
getDate	Yes"3" on page 339	Yes"3" on page 339
getDouble	Yes	Yes
getFetchDirection	Yes	Yes
getFetchSize	Yes	Yes
getFloat	Yes	Yes
getInt	Yes	Yes
getLong	Yes	Yes
getMetaData	Yes	Yes
getNClob	Yes	Yes
getNString	Yes	Yes
getObject	Yes"4" on page 339	Yes"4" on page 339
getRef	No	No
getRow	Yes	Yes
getRowId"10" on page 339	Yes	No

Table 64. Support for java.sql.ResultSet methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getShort	Yes	Yes
getStatement	Yes	Yes
getString	Yes	Yes
getTime	Yes"3" on page 339	Yes"3" on page 339
getTimestamp	Yes"3" on page 339	Yes"3" on page 339
getType	Yes	Yes
getUnicodeStream	Yes	Yes
getURL	Yes	Yes
getWarnings	Yes	Yes
insertRow	Yes	Yes
isAfterLast	Yes	Yes
isBeforeFirst	Yes	Yes
isFirst	Yes	Yes
isLast	Yes	Yes
last	Yes	Yes
moveToCurrentRow	Yes	Yes
moveToInsertRow	Yes	Yes
next	Yes	Yes
previous	Yes	Yes
refreshRow	Yes	No
relative	Yes	Yes
rowDeleted	Yes	No
rowInserted	Yes	No
rowUpdated	Yes	No
setFetchDirection	Yes	Yes
setFetchSize	Yes	Yes
updateArray	No	Yes
updateAsciiStream	Yes"5" on page 339	Yes
updateBigDecimal	Yes	Yes
updateBinaryStream	Yes"6" on page 339	Yes
updateBlob	Yes"7" on page 339	Yes
updateBoolean	Yes	Yes
updateByte	Yes	Yes
updateBytes	Yes	Yes

Table 64. Support for java.sql.ResultSet methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
updateCharacterStream	Yes"8" on page 339	Yes
updateClob	Yes"9" on page 339	Yes
updateDate	Yes	Yes
updateDouble	Yes	Yes
updateFloat	Yes	Yes
updateInt	Yes	Yes
updateLong	Yes	Yes
updateNull	Yes	Yes
updateObject	Yes	Yes
updateRef	No	No
updateRow	Yes	Yes
updateRowId"10" on page 339	Yes	No
updateShort	Yes	Yes
updateString	Yes	Yes
updateTime	Yes	Yes
updateTimestamp	Yes	Yes
wasNull	Yes	Yes

Table 64. Support for java.sql.ResultSet methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support

Notes:

1. `getBinaryStream` is not supported for CLOB columns.
2. `getMetaData` pads the schema name, if the returned schema name is less than 8 characters, to fill 8 characters.
3. The database server does no timezone adjustment for datetime values. The JDBC driver adjusts a value for the local timezone after retrieving the value from the server if you specify a form of the getDate, getTime, or getTimestamp method that includes a java.util.Calendar parameter.
4. The following form of the `getObject` method is not supported:

```
getObject(int parameterIndex, java.util.Map  map)
```

5. Supported forms of this method include the following JDBC 4.0 forms:

```
updateAsciiStream(int columnIndex, InputStream x)
updateAsciiStream(String columnLabel, InputStream x)
updateAsciiStream(int columnIndex, InputStream x, long length)
updateAsciiStream(String columnLabel, InputStream x, long length)
```

6. Supported forms of this method include the following JDBC 4.0 forms:

```
updateBinaryStream(int columnIndex, InputStream x)
updateBinaryStream(String columnLabel, InputStream x)
updateBinaryStream(int columnIndex, InputStream x, long length)
updateBinaryStream(String columnLabel, InputStream x, long length)
```

7. Supported forms of this method include the following JDBC 4.0 forms:

```
updateBlob(int columnIndex, InputStream x)
updateBlob(String columnLabel, InputStream x)
updateBlob(int columnIndex, InputStream x, long length)
updateBlob(String columnLabel, InputStream x, long length)
```

8. Supported forms of this method include the following JDBC 4.0 forms:

```
updateCharacterStream(int columnIndex, Reader reader)
updateCharacterStream(String columnLabel, Reader reader)
updateCharacterStream(int columnIndex, Reader reader, long length)
updateCharacterStream(String columnLabel, Reader reader, long length)
```

9. Supported forms of this method include the following JDBC 4.0 forms:

```
updateClob(int columnIndex, Reader reader)
updateClob(String columnLabel, Reader reader)
updateClob(int columnIndex, Reader reader, long length)
updateClob(String columnLabel, Reader reader, long length)
```

10. This is a JDBC 4.0 method.

Table 65. Support for java.sql.ResultSetMetaData methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getCatalogName	Yes	Yes
getColumnClassName	No	Yes
getColumnCount	Yes	Yes
getColumnDisplaySize	Yes	Yes

Table 65. Support for java.sql.ResultSetMetaData methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getColumnLabel	Yes	Yes
getColumnName	Yes	Yes
getColumnType	Yes	Yes
getColumnTypeName	Yes	Yes
getPrecision	Yes	Yes
getScale	Yes	Yes
getSchemaName	Yes	Yes
getTableName	Yes"1" on page 340	Yes
isAutoIncrement	Yes	Yes
isCaseSensitive	Yes	Yes
isCurrency	Yes	Yes
isDefinitelyWritable	Yes	Yes
isNullable	Yes	Yes
isReadOnly	Yes	Yes
isSearchable	Yes	Yes
isSigned	Yes	Yes
isWritable	Yes	Yes

Notes:

1. For IBM Informix data sources, `getTableName` does not return a value.
2. `getSchemaName` pads the schema name, if the returned schema name is less than 8 characters, to fill 8 characters.

Table 66. Support for java.sql.RowId methods"1" on page 340

JDBC method	IBM Data Server Driver for JDBC and SQLJ support"2" on page 340	IBM Informix JDBC Driver support
equals	Yes	No
getBytes	Yes	No
hashCode	No	No
toString	Yes	No

Notes:

1. These methods are JDBC 4.0 methods.
2. These methods are supported for connections to Db2 for z/OS, DB2 for i, and IBM Informix data sources.

Table 67. Support for java.sql.SQLClientInfoException methods[“1” on page 341]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No
getFailedProperties	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 68. Support for java.sql.SQLData methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getSQLTypeName	No	Yes
readSQL	No	Yes
writeSQL	No	Yes

Table 69. Support for java.sql.SQLDataException methods[“1” on page 341]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 70. Support for java.sql.SQLDataException methods[“1” on page 341]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 71. Support for java.sql.SQLException methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes

Table 71. Support for java.sql.SQLException methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getSQLState	Yes	Yes
getErrorCode	Yes	Yes
getNextException	Yes	Yes
setNextException	Yes	Yes

Table 72. Support for java.sql.SQLFeatureNotSupported methods[“1” on page 342]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes
Methods inherited from java.lang.Throwable	Yes	Yes
Methods inherited from java.lang.Object	Yes	Yes

Note:

1. This is a JDBC 4.0 class.

Table 73. Support for java.sql.SQLInput methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
readArray	No	Yes
readAsciiStream	No	Yes
readBigDecimal	No	Yes
readBinaryStream	No	Yes
readBlob	No	Yes
readBoolean	No	Yes
readByte	No	No
readBytes	No	No
readCharacterStream	No	No
readClob	No	Yes
readDate	No	Yes
readDouble	No	Yes
readFloat	No	Yes
readInt	No	Yes
readLong	No	Yes
readObject	No	Yes
readRef	No	No
readShort	No	Yes

Table 73. Support for java.sql.SQLInput methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
readString	No	Yes
readTime	No	Yes
readTimestamp	No	Yes
wasNull	No	Yes

Table 74. Support for java.sql.SQLIntegrityConstraintViolationException methods"1" on page 343

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes
Methods inherited from java.lang.Throwable	Yes	Yes
Methods inherited from java.lang.Object	Yes	Yes

Note:

1. This is a JDBC 4.0 class.

Table 75. Support for java.sql.SQLInvalidAuthorizationSpecException methods"1" on page 343

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes
Methods inherited from java.lang.Throwable	Yes	Yes
Methods inherited from java.lang.Object	Yes	Yes

Note:

1. This is a JDBC 4.0 class.

Table 76. Support for java.sql.SQLNonTransientConnectionException methods"1" on page 343

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 77. Support for java.sql.SQLNonTransientException methods"1" on page 344

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No

Table 77. Support for java.sql.SQLNonTransientException methods"1" on page 344 *(continued)*

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 78. Support for java.sql.SQLOutput methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
writeArray	No	No
writeAsciiStream	No	No
writeBigDecimal	No	No
writeBinaryStream	No	No
writeBlob	No	No
writeBoolean	No	No
writeByte	No	Yes
writeBytes	No	Yes
writeCharacterStream	No	No
writeClob	No	No
writeDate	No	Yes
writeDouble	No	Yes
writeFloat	No	Yes
writeInt	No	Yes
writeLong	No	No
writeObject	No	No
writeRef	No	No
writeShort	No	Yes
writeString	No	No
writeStruct	No	No
writeTime	No	Yes
writeTimestamp	No	No

Table 79. Support for java.sql.SQLRecoverableException methods"1" on page 345

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No

Table 79. Support for java.sql.SQLRecoverableException methods[“1” on page 345] *(continued)*

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 80. Support for java.sql.SQLSyntaxErrorException methods[“1” on page 345]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes
Methods inherited from java.lang.Throwable	Yes	Yes
Methods inherited from java.lang.Object	Yes	Yes

Note:

1. This is a JDBC 4.0 class.

Table 81. Support for java.sql.SQLTimeoutException methods[“1” on page 345]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes
Methods inherited from java.lang.Throwable	Yes	Yes
Methods inherited from java.lang.Object	Yes	Yes

Note:

1. This is a JDBC 4.0 class.

Table 82. Support for java.sql.SQLTransientConnectionException methods[“1” on page 345]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	Yes
Methods inherited from java.lang.Throwable	Yes	Yes
Methods inherited from java.lang.Object	Yes	Yes

Note:

1. This is a JDBC 4.0 class.

Table 83. Support for java.sql.SQLTransientException methods[“1” on page 346]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No

Table 83. Support for java.sql.SQLTransientException methods[“1” on page 346] *(continued)*

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 84. Support for java.sql.SQLTransientRollbackException methods[“1” on page 346]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
Methods inherited from java.lang.Exception	Yes	No
Methods inherited from java.lang.Throwable	Yes	No
Methods inherited from java.lang.Object	Yes	No

Note:

1. This is a JDBC 4.0 class.

Table 85. Support for java.sql.SQLXML methods[“1” on page 346]

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
free	Yes	No
getBinaryStream	Yes	No
getCharacterStream	Yes	No
getSource	Yes	No
getString	Yes	No
setBinaryStream	Yes	No
setCharacterStream	Yes	No
setResult	Yes	No
setString	Yes	No

Notes:

1. These are JDBC 4.0 methods. These methods are not supported for connections to IBM Informix servers.

Table 86. Support for java.sql.Statement methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
abort[“1” on page 348]	Yes	No
addBatch	Yes	Yes
cancel	Yes[“2” on page 348]	Yes

Table 86. Support for java.sql.Statement methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
clearBatch	Yes	Yes
clearWarnings	Yes	Yes
close	Yes	Yes
closeOnCompletion"1" on page 348	Yes	No
execute	Yes	Yes
executeBatch	Yes	Yes
executeQuery	Yes	Yes
executeUpdate	Yes	Yes
getConnection	Yes	Yes
getFetchDirection	Yes	Yes
getFetchSize	Yes	Yes
getGeneratedKeys	Yes	Yes
getMaxFieldSize	Yes	Yes
getMaxRows	Yes	Yes
getMoreResults	Yes	Yes
getQueryTimeout	Yes"7" on page 348,"5" on page 348	Yes
getResultSet	Yes	Yes
getResultSetConcurrency	Yes	Yes
getResultSetHoldability	Yes	Yes
getResultSetType	Yes	Yes
getUpdateCount"3" on page 348	Yes	Yes
getWarnings	Yes	Yes
isCloseOnCompletion"1" on page 348	Yes	No
isClosed"8" on page 348	Yes	Yes
isPoolable"8" on page 348	Yes	No
setCursorName	Yes	Yes
setEscapeProcessing	Yes	Yes
setFetchDirection	Yes	Yes
setFetchSize	Yes	Yes
setMaxFieldSize	Yes	Yes
setMaxRows	Yes	Yes
setPoolable"8" on page 348	Yes	No
setQueryTimeout	Yes"4" on page 348,"5" on page 348, "6" on page 348,"7" on page 348	Yes

Table 86. Support for java.sql.Statement methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support

Notes:

1. This is a JDBC 4.1 method.
2. For the IBM Data Server Driver for JDBC and SQLJ, `Statement.cancel` is supported only in the following environments:
   - Type 4 connectivity from a Linux, UNIX, or Windows client to a Db2 on Linux, UNIX, and Windows systems server, Version 8 or later
   - Type 2 connectivity from a Db2 on Linux, UNIX, and Windows systems client to a Db2 on Linux, UNIX, and Windows systems server, Version 8 or later
   - Type 4 connectivity from a Linux, UNIX, or Windows client to a Db2 for z/OS server, Version 9 or later.
   - Type 4 connectivity from a z/OS client to a Db2 on Linux, UNIX, and Windows systems server, Version 8 or later
   - Type 4 connectivity from a z/OS client to a Db2 for z/OS server, Version 8 or later

   The action that the IBM Data Server Driver for JDBC and SQLJ takes when the application executes `Statement.cancel` depends on the setting of the `DB2BaseDataSource.interruptProcessingMode` property.

   In addition, if `DB2BaseDataSource.interruptProcessingMode` is set to `DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL` or `DB2BaseDataSource.INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET`, and `Statement.cancel` is executed while an application is executing a method on a `ResultSet` object, the operation on the `ResultSet` object might not be canceled. When the `Statement.cancel` statement is executed, if the underlying processing for the `ResultSet` method is currently in the data server, execution of the operation is canceled. If the underlying processing for the `ResultSet` method is in the driver, execution of the operation is not canceled.
3. Not supported for stored procedure `ResultSets`.
4. For DB2 for i, this method is supported only for a *seconds* value of 0.
5. For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, `Statement.setQueryTimeout` is supported only if `Connection` or `DataSource` property queryTimeoutInterruptProcessingMode is set to INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET.
6. For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 on Linux, UNIX, and Windows systems, `Statement.setQueryTimeout` is supported only if `Connection` or `DataSource` property queryTimeoutInterruptProcessingMode is set to INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL.
7. For the IBM Data Server Driver for JDBC and SQLJ Version 4.0 and later, `Statement.setQueryTimeout` is supported for the following methods:
   - `Statement.execute`
   - `Statement.executeUpdate`
   - `Statement.executeQuery`

   `Statement.setQueryTimeout` is supported for the `Statement.executeBatch` method only when property queryTimeoutInterruptProcessingMode is set to INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET (2).
8. This is a JDBC 4.0 method.

Table 87. Support for java.sql.Struct methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getSQLTypeName	No	Yes
getAttributes	No	Yes

Table 88. Support for java.sql.Wrapper methods

JDBC method"1" on page 349	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
isWrapperFor	Yes	Yes
unWrap	Yes	Yes

Notes:

1. These are JDBC 4.0 methods.

Table 89. Support for javax.sql.XAConnection methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support"1" on page 349	IBM Informix JDBC Driver support
Methods inherited from javax.sql.PooledConnection	Yes	Yes
getXAResource	Yes	Yes

Notes:

1. These methods are supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to a Db2 on Linux, UNIX, and Windows systems server or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

Table 90. Support for javax.sql.XADataSource methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
getLoginTimeout	Yes	Yes
getLogWriter	Yes	Yes
getXAConnection	Yes	Yes
setLoginTimeout	Yes	Yes
setLogWriter	Yes	Yes

Table 91. Support for javax.transaction.xa.XAResource methods

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
commit	Yes"1" on page 350	Yes
end	Yes"1" on page 350, "2" on page 350	Yes
forget	Yes"1" on page 350	Yes
getTransactionTimeout	Yes"3" on page 350	Yes

Table 91. Support for javax.transaction.xa.XAResource methods (continued)

JDBC method	IBM Data Server Driver for JDBC and SQLJ support	IBM Informix JDBC Driver support
isSameRM	Yes"1" on page 350	Yes
prepare	Yes"1" on page 350	Yes
recover	Yes"1" on page 350	Yes
rollback	Yes"1" on page 350	Yes
setTransactionTimeout	Yes"3" on page 350	Yes
start	Yes"1" on page 350	Yes

Notes:

1. This method is supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to a Db2 on Linux, UNIX, and Windows systems server or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.
2. When the end method is called, the IBM Data Server Driver for JDBC and SQLJ closes the underlying cursor, even if the TMSUSPEND flag is specified.
3. This method is supported for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems Version 9.1 or later.

IBM Data Server Driver for JDBC and SQLJ support for SQL escape syntax

The IBM Data Server Driver for JDBC and SQLJ supports SQL escape syntax, as described in the JDBC 1.0 specification.

This is the same syntax that is used in vendor escape clauses in ODBC and CLI applications.

SQL escape syntax is supported in JDBC and SQLJ applications.

SQLJ statement reference information

SQLJ statements are used for transaction control and SQL statement execution.

SQLJ clause

The SQL statements in an SQLJ program are in SQLJ clauses.

Syntax



Usage notes

Keywords in an SQLJ clause are case sensitive, unless those keywords are part of an SQL statement in an executable clause.

Related reference

"SQLJ iterator-declaration-clause" on page 356

An iterator declaration clause declares a positioned iterator class or a named iterator class in an SQLJ application program.

"SQLJ executable-clause" on page 357
An executable clause contains an SQL statement or an assignment statement. An assignment statement assigns the result of an SQL operation to a Java variable.

"SQLJ connection-declaration-clause" on page 355
The connection declaration clause declares a connection to a data source in an SQLJ application program.

SQLJ host-expression

A host expression is a Java variable or expression that is referenced by SQLJ clauses in an SQLJ application program.

Syntax



Description

:
Indicates that the variable or expression that follows is a host expression. The colon must immediately precede the variable or expression.

IN|OUT|INOUT
For a host expression that is used as a parameter in a stored procedure call, identifies whether the parameter provides data to the stored procedure (IN), retrieves data from the stored procedure (OUT), or does both (INOUT). The default is IN.

simple-variable
Specifies a Java unqualified identifier.

complex-expression
Specifies a Java expression that results in a single value.

INDICATOR :simple-variable or INDICATOR :(complex-expression)
Specifies the optional indicator variable for the corresponding Java host variable. The data type of the indicator variable must be the Java short type. The only valid values for :simple-variable or :(complex-expression) are:

For customized applications, and for input, only these values are valid:

Indicator value	Equivalent constant	Meaning of value
-1	sqlj.runtime.ExecutionContext.DBNull	Null
-2, -3, -4, -6		Null
-5	sqlj.runtime.ExecutionContext.DBDefault	Default
-7	sqlj.runtime.ExecutionContext.DBUnassigned	Unassigned
short-value >=0	sqlj.runtime.ExecutionContext.DBNonNull	Non-null

For uncustomized applications, and for input, only these values are valid:

Indicator value	Equivalent constant	Meaning of value
-1	sqlj.runtime.ExecutionContext.DBNull	Null
-7 <= *short-value* < -1		Null
0	sqlj.runtime.ExecutionContext.DBNonNull	Non-null
short-value >0		Non-null

For customized or uncustomized applications, and for output, SQLJ sets one of these values:

Indicator value	Equivalent constant	Meaning of value
-1	sqlj.runtime.ExecutionContext.DBNull	Retrieved value is SQL NULL
0		Retrieved value is not SQL NULL

Usage notes

- A complex expression must be enclosed in parentheses.
- ANSI/ISO rules govern where a host expression can appear in a static SQL statement.
- Indicator variables are required in the following cases:
  - For input, when a Java primitive type is used to assign the NULL value to a table column.
  - For output, when a Java primitive type is used for a host variable, and the source column can return NULL values.

    If an SQL NULL value is returned, and no indicator variable is defined, an `SQLNullException` is thrown.

  Indicator variables are not required for input or output of a Java null value as an SQL NULL, if the data type of the host variable is:

  - The data type of a Java class
  - A custom database type that the driver supports
- , ... *variable-n*
- For output, indicator variables are valid in the following types of statements:
  - CALL statement with OUT or INOUT parameters
  - FETCH *positioned-iterator* INTO *variable-1*, ... *variable-n*
  - SELECT *column-1*, ... *column-n* INTO *variable-1*, ... *variable-n*

Related concepts

"Variables in SQLJ applications" on page 128
In application programs in other languages, you use host variables to pass data between the application program and the data server. In SQLJ programs, In SQLJ programs, you can use host variables or *host expressions*.

SQLJ implements-clause

The implements clause derives one or more classes from a Java interface.

Syntax



interface-element:



Description

interface-element

Specifies a user-defined Java interface, the SQLJ interface `sqlj.runtime.ForUpdate` or the SQLJ interface `sqlj.runtime.Scrollable`.

You need to implement `sqlj.runtime.ForUpdate` when you declare an iterator for a positioned UPDATE or positioned DELETE operation. See "Perform positioned UPDATE and DELETE operations in an SQLJ application" for information on performing a positioned UPDATE or positioned DELETE operation in SQLJ.

You need to implement `sqlj.runtime.Scrollable` when you declare a scrollable iterator. See "Use scrollable iterators in an SQLJ application" for information on scrollable iterators.

Related tasks

“Using scrollable iterators in an SQLJ application” on page 148
In addition to moving forward, one row at a time, through a result table, you might want to move backward or go directly to a specific row. The IBM Data Server Driver for JDBC and SQLJ provides this capability.

“Performing positioned UPDATE and DELETE operations in an SQLJ application” on page 133
As in database applications in other languages, performing positioned UPDATEs and DELETEs with SQLJ is an extension of retrieving rows from a result table.

SQLJ with-clause

The with clause specifies a set of one or more attributes for an iterator or a connection context.

Syntax



with-element:



Description

holdability
For an iterator, specifies whether an iterator keeps its position in a table after a COMMIT is executed. The value for holdability must be `true` or `false`.

sensitivity
For an iterator, specifies whether changes that are made to the underlying table can be visible to the iterator after it is opened. The value must be sqlj.runtime.ResultSetIterator.INSENSITIVE, sqlj.runtime.ResultSetIterator.SENSITIVE, or sqlj.runtime.ResultSetIterator.ASENSITIVE. The default is sqlj.runtime.ResultSetIterator.ASENSITIVE.

For connections to IBM Informix, only sqlj.runtime.ResultSetIterator.INSENSITIVE is supported.

dynamic
For an iterator that is defined with sensitivity=sqlj.runtime.ResultSetIterator.SENSITIVE, specifies whether the following cases are true:

- When the application executes positioned UPDATE and DELETE statements with the iterator, those changes are visible to the iterator.
- When the application executes INSERT, UPDATE, and DELETE statements within the application but outside the iterator, those changes are visible to the iterator.

The value for dynamic must be `true` or `false`. The default is `false`.

Db2 on Linux, UNIX, and Windows systems servers do not support dynamic scrollable cursors. Specify `true` only if your application accesses data on Db2 for z/OS servers, at Version 9 or later.

For connections to IBM Informix, only `false` is supported. IBM Informix does not support dynamic cursors.

updateColumns
For an iterator, specifies the columns that are to be modified when the iterator is used for a positioned UPDATE statement. The value for updateColumns must be a literal string that contains the column names, separated by commas.

column-name
For an iterator, specifies a column of the result table that is to be updated using the iterator.

Java-ID
For an iterator or connection context, specifies a Java variable that identifies a user-defined attribute of the iterator or connection context. The value of *Java-constant-expression* is also user-defined.

dataSource
For a connection context, specifies the logical name of a separately-created `DataSource` object that represents the data source to which the application will connect. This option is available only for the IBM Data Server Driver for JDBC and SQLJ.

Usage notes

- The value on the left side of a with element must be unique within its with clause.
- If you specify updateColumns in a with element of an iterator declaration clause, the iterator declaration clause must also contain an implements clause that specifies the sqlj.runtime.ForUpdate interface.
- If you do not customize your SQLJ program, the JDBC driver ignores the value of holdability that is in the with clause. Instead, the driver uses the JDBC driver setting for holdability.

Related concepts

"SQLJ and JDBC in the same application" on page 156
You can combine SQLJ clauses and JDBC calls in a single program.

Related tasks

"Using scrollable iterators in an SQLJ application" on page 148

In addition to moving forward, one row at a time, through a result table, you might want to move backward or go directly to a specific row. The IBM Data Server Driver for JDBC and SQLJ provides this capability.

“Performing positioned UPDATE and DELETE operations in an SQLJ application” on page 133
As in database applications in other languages, performing positioned UPDATEs and DELETEs with SQLJ is an extension of retrieving rows from a result table.

“Connecting to a data source using SQLJ” on page 121
In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

SQLJ connection-declaration-clause

The connection declaration clause declares a connection to a data source in an SQLJ application program.

Syntax



Description

Java-modifiers
Specifies modifiers that are valid for Java class declarations, such as static, public, private, or protected.

Java-class-name
Specifies a valid Java identifier. During the program preparation process, SQLJ generates a connection context class whose name is this identifier.

implements-clause
See "SQLJ implements-clause" for a description of this clause. In a connection declaration clause, the interface class to which the implements clause refers must be a user-defined interface class.

with-clause
See "SQLJ with-clause" for a description of this clause.

Usage notes

- SQLJ generates a connection class declaration for each connection declaration clause you specify. SQLJ data source connections are objects of those generated connection classes.
- You can specify a connection declaration clause anywhere that a Java class definition can appear in a Java program.

Related tasks

“Connecting to a data source using SQLJ” on page 121
In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

Related reference

“SQLJ with-clause” on page 353
The with clause specifies a set of one or more attributes for an iterator or a connection context.

“SQLJ implements-clause” on page 352

The implements clause derives one or more classes from a Java interface.

SQLJ iterator-declaration-clause

An iterator declaration clause declares a positioned iterator class or a named iterator class in an SQLJ application program.

An iterator contains the result table from a query. SQLJ generates an iterator class for each iterator declaration clause you specify. An iterator is an object of an iterator class.

An iterator declaration clause has a form for a positioned iterator and a form for a named iterator. The two kinds of iterators are distinct and incompatible Java types that are implemented with different interfaces.

Syntax



positioned-iterator-column declarations:



named-iterator-column-declarations:



Description

Java-modifiers
Any modifiers that are valid for Java class declarations, such as static, public, private, or protected.

Java-class-name
Any valid Java identifier. During the program preparation process, SQLJ generates an iterator class whose name is this identifier.

implements-clause
See "SQLJ implements-clause" for a description of this clause. For an iterator declaration clause that declares an iterator for a positioned UPDATE or positioned DELETE operation, the implements clause must specify interface `sqlj.runtime.ForUpdate`. For an iterator declaration clause that declares a scrollable iterator, the implements clause must specify interface `sqlj.runtime.Scrollable`.

with-clause
See "SQLJ with-clause" for a description of this clause.

positioned-iterator-column-declarations
Specifies a list of Java data types, which are the data types of the columns in the positioned iterator. The data types in the list must be separated by commas. The order of the data types in the positioned iterator declaration is the same as the order of the columns in the result table. For online checking during serialized profile customization to succeed, the data types of the columns in the iterator must be compatible with the data types of the columns in the result table. See "Java, JDBC, and SQL data types" for a list of compatible data types.

named-iterator-column-declarations
Specifies a list of Java data types and Java identifiers, which are the data types and names of the columns in the named iterator. Pairs of data types and names must be separated by commas. The name of a column in the iterator must match, except for case, the name of a column in the result table. For online checking during serialized profile customization to succeed, the data types of the columns in the iterator must be compatible with the data types of the columns in the result table. See "Java, JDBC, and SQL data types" for a list of compatible data types.

Usage notes

- An iterator declaration clause can appear anywhere in a Java program that a Java class declaration can appear.
- When a named iterator declaration contains more than one pair of Java data types and Java IDs, all Java IDs within the list must be unique. Two Java IDs are not unique if they differ only in case.

Related concepts

"Data retrieval in SQLJ applications" on page 142
SQLJ applications use a *result set iterator* to retrieve result sets. Like a cursor, a result set iterator can be non-scrollable or scrollable.

Related tasks

"Using scrollable iterators in an SQLJ application" on page 148
In addition to moving forward, one row at a time, through a result table, you might want to move backward or go directly to a specific row. The IBM Data Server Driver for JDBC and SQLJ provides this capability.

"Using a positioned iterator in an SQLJ application" on page 144
Use a positioned iterator to refer to columns in a result table by their position in the result set.

"Using a named iterator in an SQLJ application" on page 143
Use a named iterator to refer to each of the columns in a result table by name.

Related reference

"SQLJ with-clause" on page 353
The with clause specifies a set of one or more attributes for an iterator or a connection context.

"SQLJ implements-clause" on page 352
The implements clause derives one or more classes from a Java interface.

SQLJ executable-clause

An executable clause contains an SQL statement or an assignment statement. An assignment statement assigns the result of an SQL operation to a Java variable.

This topic describes the general form of an executable clause.

Syntax



Usage notes

- An executable clause can appear anywhere in a Java program that a Java statement can appear.
- SQLJ reports negative SQL codes from executable clauses through class `java.sql.SQLException`.

  If SQLJ raises a run-time exception during the execution of an executable clause, the value of any host expression of type OUT or INOUT is undefined.

Related reference

"SQLJ statement-clause" on page 359
A statement clause contains an SQL statement or a SET TRANSACTION clause.

"SQLJ context-clause" on page 358
A context clause specifies a connection context, an execution context, or both. You use a connection context to connect to a data source. You use an execution context to monitor and modify SQL statement execution.

"SQLJ assignment-clause" on page 362
The assignment clause assigns the result of an SQL operation to a Java variable.

SQLJ context-clause

A context clause specifies a connection context, an execution context, or both. You use a connection context to connect to a data source. You use an execution context to monitor and modify SQL statement execution.

Syntax



Description

connection-context
Specifies a valid Java identifier that is declared earlier in the SQLJ program. That identifier must be declared as an instance of the connection context class that SQLJ generates for a connection declaration clause.

execution-context
Specifies a valid Java identifier that is declared earlier in the SQLJ program. That identifier must be declared as an instance of class `sqlj.runtime.ExecutionContext`.

Usage notes

- If you do not specify a connection context in an executable clause, SQLJ uses the default connection context.
- If you do not specify an execution context, SQLJ obtains the execution context from the connection context of the statement.

Related tasks

"Controlling the execution of SQL statements in SQLJ" on page 158
You can use selected methods of the SQLJ `ExecutionContext` class to control or monitor the execution of SQL statements.

"Connecting to a data source using SQLJ" on page 121

In an SQLJ application, as in a database application in any other language, you must be connected to a data source before you can execute SQL statements.

SQLJ statement-clause

A statement clause contains an SQL statement or a SET TRANSACTION clause.

Syntax



Description

SQL-statement
You can include SQL statements in Table 92 on page 359 in a statement clause.

SET-TRANSACTION-clause
Sets the isolation level for SQL statements in the program and the access mode for the connection. The SET TRANSACTION clause is equivalent to the SET TRANSACTION statement, which is described in the ANSI/ISO SQL standard of 1992 and is supported in some implementations of SQL.

Table 92. Valid SQL statements in an SQLJ statement clause

Statement	Applicable data sources
ALTER DATABASE	"1" on page 361, "2" on page 361
ALTER FUNCTION	"1" on page 361, "2" on page 361, "3" on page 361
ALTER INDEX	"1" on page 361, "2" on page 361, "3" on page 361
ALTER PROCEDURE	"1" on page 361, "2" on page 361, "3" on page 361
ALTER STOGROUP	"1" on page 361, "2" on page 361
ALTER TABLE	"1" on page 361, "2" on page 361, "3" on page 361
ALTER TABLESPACE	"1" on page 361, "2" on page 361
CALL	"1" on page 361, "2" on page 361, "3" on page 361
COMMENT ON	"1" on page 361, "2" on page 361
COMMIT	"1" on page 361, "2" on page 361, "3" on page 361
Compound SQL (BEGIN ATOMIC...END)	"2" on page 361
CREATE ALIAS	"1" on page 361, "2" on page 361
CREATE DATABASE	"1" on page 361, "2" on page 361, "3.a" on page 361
CREATE DISTINCT TYPE	"1" on page 361, "2" on page 361, "3" on page 361
CREATE FUNCTION	"1" on page 361, "2" on page 361, "3" on page 361
CREATE GLOBAL TEMPORARY TABLE	"1" on page 361, "2" on page 361
CREATE TEMP TABLE	"3" on page 361
CREATE INDEX	"1" on page 361, "2" on page 361, "3" on page 361
CREATE PROCEDURE	"1" on page 361, "2" on page 361, "3" on page 361
CREATE STOGROUP	"1" on page 361, "2" on page 361
CREATE SYNONYM	"1" on page 361, "2" on page 361, "3" on page 361

Table 92. Valid SQL statements in an SQLJ statement clause (continued)

Statement	Applicable data sources
CREATE TABLE	“1” on page 361, “2” on page 361, “3” on page 361
CREATE TABLESPACE	“1” on page 361, “2” on page 361
CREATE TYPE (cursor)	“2” on page 361
CREATE TRIGGER	“1” on page 361, “2” on page 361, “3” on page 361
CREATE VIEW	“1” on page 361, “2” on page 361, “3” on page 361
DECLARE GLOBAL TEMPORARY TABLE	“1” on page 361, “2” on page 361
DELETE	“1” on page 361, “2” on page 361, “3” on page 361
DROP ALIAS	“1” on page 361, “2” on page 361
DROP DATABASE	“1” on page 361, “2” on page 361, “3.a” on page 361
DROP DISTINCT TYPE	“1” on page 361, “2” on page 361
DROP TYPE	“3” on page 361
DROP FUNCTION	“1” on page 361, “2” on page 361, “3” on page 361
DROP INDEX	“1” on page 361, “2” on page 361, “3” on page 361
DROP PACKAGE	“1” on page 361, “2” on page 361
DROP PROCEDURE	“1” on page 361, “2” on page 361, “3” on page 361
DROP STOGROUP	“1” on page 361, “2” on page 361
DROP SYNONYM	“1” on page 361, “2” on page 361, “3” on page 361
DROP TABLE	“1” on page 361, “2” on page 361, “3” on page 361
DROP TABLESPACE	“1” on page 361, “2” on page 361
DROP TRIGGER	“1” on page 361, “2” on page 361, “3” on page 361
DROP VIEW	“1” on page 361, “2” on page 361, “3” on page 361
FETCH	“1” on page 361, “2” on page 361, “3” on page 361
GRANT	“1” on page 361, “2” on page 361, “3” on page 361
INSERT	“1” on page 361, “2” on page 361, “3” on page 361
LOCK TABLE	“1” on page 361, “2” on page 361, “3” on page 361
MERGE	“1” on page 361, “2” on page 361
REVOKE	“1” on page 361, “2” on page 361, “3” on page 361
ROLLBACK	“1” on page 361, “2” on page 361, “3” on page 361
SAVEPOINT	“1” on page 361, “2” on page 361, “3” on page 361
SELECT INTO	“1” on page 361, “2” on page 361, “3” on page 361
SET CURRENT APPLICATION ENCODING SCHEME	“1” on page 361
SET CURRENT DEBUG MODE	“1” on page 361
SET CURRENT DEFAULT TRANSFORM GROUP	“2” on page 361
SET CURRENT DEGREE	“1” on page 361, “2” on page 361

Table 92. Valid SQL statements in an SQLJ statement clause (continued)

Statement	Applicable data sources
SET CURRENT EXPLAIN MODE	"2" on page 361
SET CURRENT EXPLAIN SNAPSHOT	"2" on page 361
SET CURRENT ISOLATION	"1" on page 361, "2" on page 361
SET CURRENT LOCALE LC_CTYPE	"1" on page 361
SET CURRENT MAINTAINED TABLE TYPES FOR OPTIMIZATION	"1" on page 361, "2" on page 361
SET CURRENT OPTIMIZATION HINT	"1" on page 361, "2" on page 361
SET CURRENT PACKAGE PATH	"1" on page 361
SET CURRENT PACKAGESET (USER is not supported)	"1" on page 361, "2" on page 361
SET CURRENT PRECISION	"1" on page 361, "2" on page 361
SET CURRENT QUERY ACCELERATION	"1" on page 361
SET CURRENT QUERY OPTIMIZATION	"2" on page 361
SET CURRENT REFRESH AGE	"1" on page 361, "2" on page 361
SET CURRENT ROUTINE VERSION	"1" on page 361
SET CURRENT RULES	"1" on page 361
SET CURRENT SCHEMA	"2" on page 361
SET CURRENT SQLID	"1" on page 361
SET PATH	"1" on page 361, "2" on page 361
TRUNCATE	"1" on page 361
UPDATE	"1" on page 361, "2" on page 361, "3" on page 361

Note: The SQL statement applies to connections to the following data sources:

1. Db2 for z/OS
2. Db2 on Linux, UNIX, and Windows systems
3. IBM Informix
   a. IBM Informix, for the SYSMASTER database only.

Usage notes

- SQLJ supports both positioned and searched DELETE and UPDATE operations.
- For a FETCH statement, a positioned DELETE statement, or a positioned UPDATE statement, you must use an iterator to refer to rows in a result table.

Related tasks

"Setting the isolation level for an SQLJ transaction" on page 171
To set the isolation level for a unit of work within an SQLJ program, use the SET TRANSACTION ISOLATION LEVEL clause.

Related reference

"SQLJ SET-TRANSACTION-clause" on page 362
The SET TRANSACTION clause sets the isolation level for the current unit of work.

Statements (Db2 SQL)

SQLJ SET-TRANSACTION-clause

The SET TRANSACTION clause sets the isolation level for the current unit of work.

Syntax



Description

ISOLATION LEVEL
Specifies one of the following isolation levels:

READ COMMITTED
Specifies that the current isolation level is cursor stability.

READ UNCOMMITTED
Specifies that the current isolation level is uncommitted read.

REPEATABLE READ
Specifies that the current isolation level is read stability.

SERIALIZABLE
Specifies that the current isolation level is repeatable read.

Usage notes

You can execute SET TRANSACTION only at the beginning of a transaction.

Related tasks
"Setting the isolation level for an SQLJ transaction" on page 171
To set the isolation level for a unit of work within an SQLJ program, use the SET TRANSACTION ISOLATION LEVEL clause.

SQLJ assignment-clause

The assignment clause assigns the result of an SQL operation to a Java variable.

Syntax



Description

Java-ID
Identifies an iterator that was declared previously as an instance of an iterator class.

fullselect
Generates a result table.

iterator-conversion-clause
See "SQLJ iterator-conversion-clause" for a description of this clause.

Usage notes

- If the object that is identified by *Java-ID* is a positioned iterator, the number of columns in the result set must match the number of columns in the iterator. In addition, the data type of each column in the result set must be compatible with the data type of the corresponding column in the iterator. See "Java, JDBC, and SQL data types" for a list of compatible Java and SQL data types.
- If the object that is identified by *Java-ID* is a named iterator, the name of each accessor method must match, except for case, the name of a column in the result set. In addition, the data type of the object that an accessor method returns must be compatible with the data type of the corresponding column in the result set.
- You can put an assignment clause anywhere in a Java program that a Java assignment statement can appear. However, you cannot put an assignment clause where a Java assignment expression can appear. For example, you cannot specify an assignment clause in the control list of a for statement.

Related concepts
"SQLJ and JDBC in the same application" on page 156
You can combine SQLJ clauses and JDBC calls in a single program.

Related reference
"SQLJ iterator-conversion-clause" on page 363
The iterator conversion clause converts a JDBC `ResultSet` to an iterator.

SQLJ iterator-conversion-clause

The iterator conversion clause converts a JDBC `ResultSet` to an iterator.

Syntax



Description

host-expression
Identifies the JDBC `ResultSet` that is to be converted to an SQLJ iterator.

Usage notes

- If the iterator to which the JDBC `ResultSet` is to be converted is a positioned iterator, the number of columns in the `ResultSet` must match the number of columns in the iterator. In addition, the data type of each column in the `ResultSet` must be compatible with the data type of the corresponding column in the iterator.
- If the iterator is a named iterator, the name of each accessor method must match, except for case, the name of a column in the `ResultSet`. In addition, the data type of the object that an accessor method returns must be compatible with the data type of the corresponding column in the `ResultSet`.
- When an iterator that is generated through the iterator conversion clause is closed, the `ResultSet` from which the iterator is generated is also closed.

Related concepts
"SQLJ and JDBC in the same application" on page 156

You can combine SQLJ clauses and JDBC calls in a single program.

Interfaces and classes in the sqlj.runtime package

The sqlj.runtime package defines the run-time classes and interfaces that are used directly or indirectly by the SQLJ programmer.

Classes such as `AsciiStream` are used directly by the SQLJ programmer. Interfaces such as `ResultSetIterator` are implemented as part of generated class declarations.

sqlj.runtime interfaces

The following table summarizes the interfaces in sqlj.runtime.

Table 93. Summary of sqlj.runtime interfaces

Interface name	Purpose
ConnectionContext	Manages the SQL operations that are performed during a connection to a data source.
ForUpdate	Implemented by iterators that are used in a positioned UPDATE or DELETE statement.
NamedIterator	Implemented by iterators that are declared as named iterators.
PositionedIterator	Implemented by iterators that are declared as positioned iterators.
ResultSetIterator	Implemented by all iterators to allow query results to be processed using a JDBC `ResultSet`.
Scrollable	Provides a set of methods for manipulating scrollable iterators.

sqlj.runtime classes

The following table summarizes the classes in sqlj.runtime.

Table 94. Summary of sqlj.runtime classes

Class name	Purpose
AsciiStream	A class for handling an input stream whose bytes should be interpreted as ASCII.
BinaryStream	A class for handling an input stream whose bytes should be interpreted as binary.
CharacterStream	A class for handling an input stream whose bytes should be interpreted as Character.
DefaultRuntime	Implemented by SQLJ to satisfy the expected runtime behavior of SQLJ for most JVM environments. This class is for internal use only and is not described in this documentation.
ExecutionContext	Implemented when an SQLJ execution context is declared, to control the execution of SQL operations.
Indicator	Defines constants for indicator variable values.
RuntimeContext	Defines system-specific services that are provided by the runtime environment. This class is for internal use only and is not described in this documentation.
SQLNullException	Derived from the `java.sql.SQLException` class. An `sqlj.runtime.SQLNullException` is thrown when an SQL NULL value is fetched into a host identifier with a Java primitive type.

Table 94. Summary of sqlj.runtime classes (continued)

Class name	Purpose
StreamWrapper	Wraps a `java.io.InputStream` instance.
UnicodeStream	A class for handling an input stream whose bytes should be interpreted as Unicode.

sqlj.runtime.ConnectionContext interface

The `sqlj.runtime.ConnectionContext` interface provides a set of methods that manage SQL operations that are performed during a session with a specific data source.

Translation of an SQLJ connection declaration clause causes SQLJ to create a connection context class. A connection context object maintains a JDBC `Connection` object on which dynamic SQL operations can be performed. A connection context object also maintains a default `ExecutionContext` object.

Variables

CLOSE_CONNECTION

Format:

```
public static final boolean CLOSE_CONNECTION=true;
```

A constant that can be passed to the close method. It indicates that the underlying JDBC Connection object should be closed.

KEEP_CONNECTION

Format:

```
public static final boolean KEEP_CONNECTION=false;
```

A constant that can be passed to the close method. It indicates that the underlying JDBC Connection object should not be closed.

Methods

close()

Format:

```
public abstract void close() throws SQLException
```

Performs the following functions:

- Releases all resources that are used by the given connection context object
- Closes any open `ConnectedProfile` objects
- Closes the underlying JDBC `Connection` object

close() is equivalent to close(CLOSE_CONNECTION).

close(boolean)

Format:

```
public abstract void close (boolean close-connection)
 throws SQLException
```

Performs the following functions:

- Releases all resources that are used by the given connection context object
- Closes any open `ConnectedProfile` objects

- Closes the underlying JDBC `Connection` object, depending on the value of the *close-connection* parameter

Parameters:

close-connection
Specifies whether the underlying JDBC `Connection` object is closed when a connection context object is closed:

CLOSE_CONNECTION
Closes the underlying JDBC `Connection` object.

KEEP_CONNECTION
Does not close the underlying JDBC `Connection` object.

getConnectedProfile
Format:

```
public abstract ConnectedProfile getConnectedProfile(Object profileKey)
 throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

getConnection
Format:

```
public abstract Connection getConnection()
```

Returns the underlying JDBC `Connection` object for the given connection context object.

getExecutionContext
Format:

```
public abstract ExecutionContext getExecutionContext()
```

Returns the default `ExecutionContext` object that is associated with the given connection context object.

isClosed
Format:

```
public abstract boolean isClosed()
```

Returns `true` if the given connection context object has been closed. Returns `false` if the connection context object has not been closed.

Constructors

The following constructors are defined in a concrete implementation of the `ConnectionContext` interface that results from translation of the statement `#sql context Ctx;`:

Ctx(String, boolean)
Format:

```
public Ctx(String url, boolean autocommit)
 throws SQLException
```

Parameters:

url
The representation of a data source, as specified in the JDBC getConnection method.

autocommit
Whether autocommit is enabled for the connection. A value of `true` means that autocommit is enabled. A value of `false` means that autocommit is disabled.

Ctx(String, String, String, boolean)

Format:

```
public Ctx(String url, String user, String password,
 boolean autocommit)
 throws SQLException
```

Parameters:

url
The representation of a data source, as specified in the JDBC getConnection method.

user
The user ID under which the connection to the data source is made.

password
The password for the user ID under which the connection to the data source is made.

autocommit
Whether autocommit is enabled for the connection. A value of `true` means that autocommit is enabled. A value of `false` means that autocommit is disabled.

Ctx(String, Properties, boolean)

Format:

```
public Ctx(String url, Properties info, boolean autocommit)
 throws SQLException
```

Parameters:

url
The representation of a data source, as specified in the JDBC getConnection method.

info
An object that contains a set of driver properties for the connection. Any of the IBM Data Server Driver for JDBC and SQLJ properties can be specified.

autocommit
Whether autocommit is enabled for the connection. A value of `true` means that autocommit is enabled. A value of `false` means that autocommit is disabled.

Ctx(Connection)

Format:

```
public Ctx(java.sql.Connection JDBC-connection-object)
 throws SQLException
```

Parameters:

JDBC-connection-object
A previously created JDBC `Connection` object.

If the constructor call throws an SQLException, the JDBC `Connection` object remains open.

Ctx(ConnectionContext)

Format:

```
public Ctx(sqlj.runtime.ConnectionContext SQLJ-connection-context-object)
 throws SQLException
```

Parameters:

SQLJ-connection-context-object
A previously created SQLJ `ConnectionContext` object.

The following constructors are defined in a concrete implementation of the `ConnectionContext` interface that results from translation of the statement `#sql context Ctx with (dataSource ="jdbc/TestDS");`:

Ctx()

Format:

```
public Ctx()
 throws SQLException
```

Ctx(String, String)

Format:

```
public Ctx(String user, String password,
)
 throws SQLException
```

Parameters:

user
The user ID under which the connection to the data source is made.

password
The password for the user ID under which the connection to the data source is made.

Ctx(Connection)

Format:

```
public Ctx(java.sql.Connection JDBC-connection-object)
 throws SQLException
```

Parameters:

JDBC-connection-object
A previously created JDBC `Connection` object.

If the constructor call throws an SQLException, the JDBC `Connection` object remains open.

Ctx(ConnectionContext)

Format:

```
public Ctx(sqlj.runtime.ConnectionContext SQLJ-connection-context-object)
 throws SQLException
```

Parameters:

SQLJ-connection-context-object
A previously created SQLJ `ConnectionContext` object.

Additional methods

The following additional methods are generated in a concrete implementation of the `ConnectionContext` interface that results from translation of the statement `#sql context Ctx;`:

getDefaultContext

Format:

```
public static Ctx getDefaultContext()
```

Returns the default connection context object for the Ctx class.

getProfileKey

Format:

```
public static Object getProfileKey(sqlj.runtime.profile.Loader loader,
String profileName) throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

getProfile
Format:

```
public static sqlj.runtime.profile.Profile getProfile(Object key)
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

getTypeMap
Format:

```
public static java.util.Map getTypeMap()
```

Returns an instance of a class that implements `java.util.Map`, which is the user-defined type map that is associated with the `ConnectionContext`. If there is no associated type map, Java null is returned.

This method is used by code that is generated by the SQLJ translator for executable clauses and iterator declaration clauses, but it can also be invoked in an SQLJ application for direct use in JDBC statements.

SetDefaultContext
Format:

```
public static void Ctx setDefaultContext(Ctx default-context)
```

Sets the default connection context object for the Ctx class.

Recommendation: Do not use this method for multithreaded applications. Instead, use explicit contexts.

sqlj.runtime.ForUpdate interface

SQLJ implements the `sqlj.runtime.ForUpdate` interface in SQLJ programs that contain an iterator declaration clause with `implements sqlj.runtime.ForUpdate`.

An SQLJ program that does positioned UPDATE or DELETE operations (UPDATE...WHERE CURRENT OF or DELETE...WHERE CURRENT OF) must include an iterator declaration clause with `implements sqlj.runtime.ForUpdate`.

Methods

getCursorName
Format:

```
public abstract String getCursorName() throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

sqlj.runtime.NamedIterator interface

The `sqlj.runtime.NamedIterator` interface is implemented when an SQLJ application executes an iterator declaration clause for a named iterator.

A named iterator includes result table column names, and the order of the columns in the iterator is not important.

An implementation of the `sqlj.runtime.NamedIterator` interface includes an accessor method for each column in the result table. An accessor method returns the data from its column of the result table. The name of an accessor method matches the name of the corresponding column in the named iterator.

Methods (inherited from the `ResultSetIterator` interface)

close
Format:

```
public abstract void close() throws SQLException
```

Releases database resources that the iterator uses.

isClosed
Format:

```
public abstract boolean isClosed() throws SQLException
```

Returns a value of `true` if the close method has been invoked. Returns `false` if the close method has not been invoked.

next
Format:

```
public abstract boolean next() throws SQLException
```

Advances the iterator to the next row. Before an instance of the `next` method is invoked for the first time, the iterator is positioned before the first row of the result table. `next` returns a value of `true` when a next row is available and `false` when all rows have been retrieved.

sqlj.runtime.PositionedIterator interface

The `sqlj.runtime.PositionedIterator` interface is implemented when an SQLJ application executes an iterator declaration clause for a positioned iterator.

The order of columns in a positioned iterator must be the same as the order of columns in the result table, and a positioned iterator does not include result table column names.

Methods

`sqlj.runtime.PositionedIterator` inherits all **ResultSetIterator** methods, and includes the following additional method:

endFetch
Format:

```
public abstract boolean endFetch() throws SQLException
```

Returns a value of `true` if the iterator is not positioned on a row. Returns a value of `false` if the iterator is positioned on a row.

sqlj.runtime.ResultSetIterator interface

The `sqlj.runtime.ResultSetIterator` interface is implemented by SQLJ for all iterator declaration clauses.

An untyped iterator can be generated by declaring an instance of the `sqlj.runtime.ResultSetIterator` interface directly. In general, use of untyped iterators is not recommended.

Variables

ASENSITIVE
Format:

```
public static final int ASENSITIVE
```

A constant that can be returned by the getSensitivity method. It indicates that the iterator is defined as ASENSITIVE.

This value is not returned by IBM Informix.

FETCH_FORWARD
Format:

```
public static final int FETCH_FORWARD
```

A constant that can be used by the following methods:

- Set by sqlj.runtime.Scrollable.setFetchDirection and sqlj.runtime.ExecutionContext.setFetchDirection
- Returned by sqlj.runtime.ExecutionContext.getFetchDirection

It indicates that the iterator fetches rows in a result table in the forward direction, from first to last.

FETCH_REVERSE
Format:

```
public static final int FETCH_REVERSE
```

A constant that can be used by the following methods:

- Set by sqlj.runtime.Scrollable.setFetchDirection and sqlj.runtime.ExecutionContext.setFetchDirection
- Returned by sqlj.runtime.ExecutionContext.getFetchDirection

It indicates that the iterator fetches rows in a result table in the backward direction, from last to first.

This value is not returned by IBM Informix.

FETCH_UNKNOWN
Format:

```
public static final int FETCH_UNKNOWN
```

A constant that can be used by the following methods:

- Set by sqlj.runtime.Scrollable.setFetchDirection and sqlj.runtime.ExecutionContext.setFetchDirection
- Returned by sqlj.runtime.ExecutionContext.getFetchDirection

It indicates that the iterator fetches rows in a result table in an unknown order.

This value is not returned by IBM Informix.

INSENSITIVE
Format:

```
public static final int INSENSITIVE
```

A constant that can be returned by the getSensitivity method. It indicates that the iterator is defined as INSENSITIVE.

SENSITIVE
Format:

```
public static final int SENSITIVE
```

A constant that can be returned by the getSensitivity method. It indicates that the iterator is defined as SENSITIVE.

This value is not returned by IBM Informix.

Methods

clearWarnings

Format:

```
public abstract void clearWarnings() throws SQLException
```

After clearWarnings is called, getWarnings returns null until a new warning is reported for the iterator.

close

Format:

```
public abstract void close() throws SQLException
```

Closes the iterator and releases underlying database resources.

getFetchSize

Format:

```
synchronized public int getFetchSize() throws SQLException
```

Returns the number of rows that should be fetched by SQLJ when more rows are needed. The returned value is the value that was set by the setFetchSize method, or 0 if no value was set by setFetchSize.

getResultSet

Format:

```
public abstract ResultSet getResultSet() throws SQLException
```

Returns the JDBC `ResultSet` object that is associated with the iterator.

getRow

Format:

```
synchronized public int getRow() throws SQLException
```

Returns the current row number. The first row is number 1, the second is number 2, and so on. If the iterator is not positioned on a row, 0 is returned.

getSensitivity

Format:

```
synchronized public int getSensitivity() throws SQLException
```

Returns the sensitivity of the iterator. The sensitivity is determined by the sensitivity value that was specified or defaulted in the with clause of the iterator declaration clause.

getWarnings

Format:

```
public abstract SQLWarning getWarnings() throws SQLException
```

Returns the first warning that is reported by calls on the iterator. Subsequent iterator warnings are be chained to this SQLWarning. The warning chain is automatically cleared each time the iterator moves to a new row.

isClosed

Format:

```
public abstract boolean isClosed() throws SQLException
```

Returns a value of `true` if the iterator is closed. Returns `false` otherwise.

next
Format:

```
public abstract boolean next() throws SQLException
```

Advances the iterator to the next row. Before `next` is invoked for the first time, the iterator is positioned before the first row of the result table. `next` returns a value of `true` when a next row is available and `false` when all rows have been retrieved.

setFetchSize
Format:

```
synchronized public void setFetchSize(int number-of-rows) throws SQLException
```

Gives SQLJ a hint as to the number of rows that should be fetched when more rows are needed.

Parameters:

number-of-rows
The expected number of rows that SQLJ should fetch for the iterator that is associated with the given execution context.

If *number-of-rows* is less than 0 or greater than the maximum number of rows that can be fetched, an SQLException is thrown.

sqlj.runtime.Scrollable interface

`sqlj.runtime.Scrollable` provides methods to move around in the result table and to check the position in the result table.

`sqlj.runtime.Scrollable` is implemented when a scrollable iterator is declared.

Methods

absolute(int)
Format:

```
public abstract boolean absolute (int n) throws SQLException
```

Moves the iterator to a specified row.

If *n*>0, positions the iterator on row *n* of the result table. If *n*<0, and *m* is the number of rows in the result table, positions the iterator on row *m+n+1* of the result table.

If the absolute value of *n* is greater than the number of rows in the result table, positions the cursor after the last row if *n* is positive, or before the first row if *n* is negative.

`absolute(0)` is the same as `beforeFirst()`. `absolute(1)` is the same as `first()`. `absolute(-1)` is the same as `last()`.

Returns `true` if the iterator is on a row. Otherwise, returns `false`.

afterLast()
Format:

```
public abstract void afterLast() throws SQLException
```

Moves the iterator after the last row of the result table.

beforeFirst()
Format:

```
public abstract void beforeFirst() throws SQLException
```

Moves the iterator before the first row of the result table.

first()
Format:

```
public abstract boolean first() throws SQLException
```

Moves the iterator to the first row of the result table.

Returns `true` if the iterator is on a row. Otherwise, returns `false`.

getFetchDirection()
Format:

```
public abstract int getFetchDirection() throws SQLException
```

Returns the fetch direction of the iterator. Possible values are:

sqlj.runtime.ResultSetIterator.FETCH_FORWARD
Rows are processed in a forward direction, from first to last.

sqlj.runtime.ResultSetIterator.FETCH_REVERSE
Rows are processed in a backward direction, from last to first.

sqlj.runtime.ResultSetIterator.FETCH_UNKNOWN
The order of processing is not known.

isAfterLast()
Format:

```
public abstract boolean isAfterLast() throws SQLException
```

Returns `true` if the iterator is positioned after the last row of the result table. Otherwise, returns `false`.

isBeforeFirst()
Format:

```
public abstract boolean isBeforeFirst() throws SQLException
```

Returns `true` if the iterator is positioned before the first row of the result table. Otherwise, returns `false`.

isFirst()
Format:

```
public abstract boolean isFirst() throws SQLException
```

Returns `true` if the iterator is positioned on the first row of the result table. Otherwise, returns `false`.

isLast()
Format:

```
public abstract boolean isLast() throws SQLException
```

Returns `true` if the iterator is positioned on the last row of the result table. Otherwise, returns `false`.

last()
Format:

```
public abstract boolean last() throws SQLException
```

Moves the iterator to the last row of the result table.

Returns `true` if the iterator is on a row. Otherwise, returns `false`.

previous()
Format:

```
public abstract boolean previous() throws SQLException
```

Moves the iterator to the previous row of the result table.

Returns `true` if the iterator is on a row. Otherwise, returns `false`.

relative(int)
Format:

```
public abstract boolean relative(int n) throws SQLException
```

If *n*>0, positions the iterator on the row that is *n* rows after the current row. If *n*<0, positions the iterator on the row that is *n* rows before the current row. If *n*=0, positions the iterator on the current row.

The cursor must be on a valid row of the result table before you can use this method. If the cursor is before the first row or after the last throw, the method throws an `SQLException`.

Suppose that *m* is the number of rows in the result table and *x* is the current row number in the result table. If *n*>0 and *x*+*n*>*m*, the iterator is positioned after the last row. If *n*<0 and *x*+*n*<1, the iterator is positioned before the first row.

Returns `true` if the iterator is on a row. Otherwise, returns `false`.

setFetchDirection(int)
Format:

```
public abstract void setFetchDirection (int) throws SQLException
```

Gives the SQLJ runtime environment a hint as to the direction in which rows of this iterator object are processed. Possible values are:

sqlj.runtime.ResultSetIterator.FETCH_FORWARD
Rows are processed in a forward direction, from first to last.

sqlj.runtime.ResultSetIterator.FETCH_REVERSE
Rows are processed in a backward direction, from last to first.

sqlj.runtime.ResultSetIterator.FETCH_UNKNOWN
The order of processing is not known.

sqlj.runtime.AsciiStream class

The `sqlj.runtime.AsciiStream` class is for an input stream of ASCII data with a specified length.

The `sqlj.runtime.AsciiStream` class is derived from the `java.io.InputStream` class, and extends the `sqlj.runtime.StreamWrapper` class. SQLJ interprets the bytes in an `sqlj.runtime.AsciiStream` object as ASCII characters. An InputStream object with ASCII characters needs to be passed as a `sqlj.runtime.AsciiStream` object.

Constructors

AsciiStream(InputStream)
Format:

```
public AsciiStream(java.io.InputStream input-stream)
```

Creates an ASCII `java.io.InputStream` object with an unspecified length.

Parameters:

input-stream
The `InputStream` object that SQLJ interprets as an `AsciiStream` object.

AsciiStream(InputStream, int)
Format:

```
public AsciiStream(java.io.InputStream input-stream, int length)
```

Creates an ASCII `java.io.InputStream` object with a specified length.

Parameters:

input-stream
The `InputStream` object that SQLJ interprets as an `AsciiStream` object.

length
The length of the `InputStream` object that SQLJ interprets as an `AsciiStream` object.

sqlj.runtime.BinaryStream class

The `sqlj.runtime.BinaryStream` class is for an input stream of binary data with a specified length.

The `sqlj.runtime.BinaryStream` class is derived from the java.io.InputStream class, and extends the `sqlj.runtime.StreamWrapper` class. SQLJ interprets the bytes in an `sqlj.runtime.BinaryStream` object are interpreted as Binary characters. An InputStream object with Binary characters needs to be passed as a `sqlj.runtime.BinaryStream` object.

Constructors

BinaryStream(InputStream)
Format:

```
public BinaryStream(java.io.InputStream input-stream)
```

Creates an Binary `java.io.InputStream` object with an unspecified length.

Parameters:

input-stream
The `InputStream` object that SQLJ interprets as an `BinaryStream` object.

BinaryStream(InputStream, int)
Format:

```
public BinaryStream(java.io.InputStream input-stream, int length)
```

Creates an Binary `java.io.InputStream` object with a specified length.

Parameters:

input-stream
The `InputStream` object that SQLJ interprets as an `BinaryStream` object.

length
The length of the `InputStream` object that SQLJ interprets as an `BinaryStream` object.

sqlj.runtime.CharacterStream class

The `sqlj.runtime.CharacterStream` class is for an input stream of character data with a specified length.

The `sqlj.runtime.CharacterStream` class is derived from the java.io.Reader class, and extends the `java.io.FilterReader` class. SQLJ interprets the bytes in an `sqlj.runtime.CharacterStream` object are interpreted as Unicode data. A `Reader` object with Unicode data needs to be passed as a `sqlj.runtime.CharacterStream` object.

Constructors

CharacterStream(InputStream)
Format:

```
public CharacterStream(java.io.Reader input-stream)
```

Creates a character `java.io.Reader` object with an unspecified length.

Parameters:

input-stream
The `Reader` object that SQLJ interprets as an `CharacterStream` object.

CharacterStream(InputStream, int)
Format:

```
public CharacterStream(java.io.Reader input-stream, int length)
```

Creates a character `java.io.Reader` object with a specified length.

Parameters:

input-stream
The `Reader` object that SQLJ interprets as an `CharacterStream` object.

length
The length of the `Reader` object that SQLJ interprets as an `CharacterStream` object.

Methods

getReader
Format:

```
public Reader getReader()
```

Returns the underlying `Reader` object that is wrapped by the `CharacterStream` object.

getLength
Format:

```
public void getLength()
```

Returns the length in characters of the wrapped `Reader` object, as specified by the constructor or in the last call to setLength.

setLength
Format:

```
public void setLength (int length)
```

Sets the number of characters that are read from the `Reader` object when the object is passed as an input argument to an SQL operation.

Parameters:

length
The number of characters that are read from the `Reader` object.

sqlj.runtime.ExecutionContext class

The `sqlj.runtime.ExecutionContext` class is defined for execution contexts. An execution context is used to control the execution of SQL statements.

Variables

ADD_BATCH_COUNT
Format:

```
public static final int ADD_BATCH_COUNT
```

A constant that can be returned by the getUpdateCount method. It indicates that the previous statement was not executed but was added to the existing statement batch.

AUTO_BATCH
Format:

```
public static final int AUTO_BATCH
```

A constant that can be passed to the setBatchLimit method. It indicates that implicit batch execution should be performed, and that SQLJ should determine the batch size.

DBDefault
Format:

```
public static final short DBDefault=-5;
```

A constant that can be assigned to an indicator variable. It specifies that the corresponding host variable value that is passed to the data server is the default value.

DBNonNull
Format:

```
public static final short DBNonNull=0;
```

A constant that can be assigned to an indicator variable. It specifies that the corresponding host variable value that is passed to the data server is a non-null value.

DBNull
Format:

```
public static final short DBNull=-1;
```

A constant that can be assigned to an indicator variable. It specifies that the corresponding host variable value that is passed to the data server is the SQL NULL value.

DBUnassigned
Format:

```
public static final short DBUnassigned=-7;
```

A constant that can be assigned to an indicator variable. It specifies that no value for the corresponding host variable is passed to the data server.

EXEC_BATCH_COUNT
Format:

```
public static final int EXEC_BATCH_COUNT
```

A constant that can be returned from the getUpdateCount method. It indicates that a statement batch was just executed.

EXCEPTION_COUNT
Format:

```
public static final int EXCEPTION_COUNT
```

A constant that can be returned from the getUpdateCount method. It indicates that an exception was thrown before the previous execution completed, or that no operation has been performed on the execution context object.

NEW_BATCH_COUNT
Format:

```
public static final int NEW_BATCH_COUNT
```

A constant that can be returned from the getUpdateCount method. It indicates that the previous statement was not executed, but was added to a new statement batch.

QUERY_COUNT
Format:

```
public static final int QUERY_COUNT
```

A constant that can be passed to the setBatchLimit method. It indicates that the previous execution produced a result set.

UNLIMITED_BATCH
Format:

```
public static final int UNLIMITED_BATCH
```

A constant that can be returned from the getUpdateCount method. It indicates that statements should continue to be added to a statement batch, regardless of the batch size.

Constructors:

ExecutionContext
Format:

```
public ExecutionContext()
```

Creates an `ExecutionContext` instance.

Methods

cancel
Format:

```
public void cancel() throws SQLException
```

Cancels an SQL operation that is currently being executed by a thread that uses the execution context object. If there is a pending statement batch on the execution context object, the statement batch is canceled and cleared.

The cancel method throws an SQLException if the statement cannot be canceled.

execute
Format:

```
public boolean execute ( ) throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

executeBatch
Format:

```
public synchronized int[] executeBatch() throws SQLException
```

Executes the pending statement batch and returns an array of update counts. If no pending statement batch exists, null is returned. When this method is called, the statement batch is cleared, even if the call results in an exception.

Each element in the returned array can be one of the following values:

-2
This value indicates that the SQL statement executed successfully, but the number of rows that were updated could not be determined.

-3
This value indicates that the SQL statement failed.

Other integer
This value is the number of rows that were updated by the statement.

The executeBatch method throws an SQLException if a database error occurs while the statement batch executes.

executeQuery
Format:

```
public RTResultSet executeQuery ( ) throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

executeUpdate
Format:

```
public int executeUpdate() throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

getBatchLimit
Format:

```
synchronized public int getBatchLimit()
```

Returns the number of statements that are added to a batch before the batch is implicitly executed.

The returned value is one of the following values:

UNLIMITED_BATCH
This value indicates that the batch size is unlimited.

AUTO_BATCH
This value indicates that the batch size is finite but unknown.

Other integer
The current batch limit.

getBatchUpdateCounts
Format:

```
public synchronized int[] getBatchUpdateCounts()
```

Returns an array that contains the number of rows that were updated by each statement that successfully executed in a batch. The order of elements in the array corresponds to the order in which statements were inserted into the batch. Returns null if no statements in the batch completed successfully.

Each element in the returned array can be one of the following values:

-2
This value indicates that the SQL statement executed successfully, but the number of rows that were updated could not be determined.

-3
This value indicates that the SQL statement failed.

Other integer
This value is the number of rows that were updated by the statement.

getFetchDirection
Format:

```
synchronized public int getFetchDirection() throws SQLException
```

Returns the current fetch direction for scrollable iterator objects that were generated from the given execution context. If a fetch direction was not set for the execution context, sqlj.runtime.ResultSetIterator.FETCH_FORWARD is returned.

getFetchSize

Format:

```
synchronized public int getFetchSize() throws SQLException
```

Returns the number of rows that should be fetched by SQLJ when more rows are needed. This value applies only to iterator objects that were generated from the given execution context. The returned value is the value that was set by the setFetchSize method, or 0 if no value was set by setFetchSize.

getMaxFieldSize

Format:

```
public synchronized int getMaxFieldSize()
```

Returns the maximum number of bytes that are returned for any string (character, graphic, or varying-length binary) column in queries that use the given execution context. If this limit is exceeded, SQLJ discards the remaining bytes. A value of 0 means that the maximum number of bytes is unlimited.

getMaxRows

Format:

```
public synchronized int getMaxRows()
```

Returns the maximum number of rows that are returned for any query that uses the given execution context. If this limit is exceeded, SQLJ discards the remaining rows. A value of 0 means that the maximum number of rows is unlimited.

getNextResultSet()

Format:

```
public ResultSet getNextResultSet() throws SQLException
```

After a stored procedure call, returns a result set from the stored procedure.

A null value is returned if any of the following conditions are true:

- There are no more result sets to be returned.
- The stored procedure call did not produce any result sets.
- A stored procedure call has not been executed under the execution context.

When you invoke `getNextResultSet()`, SQLJ closes the currently-open result set and advances to the next result set.

If an error occurs during a call to getNextResultSet, resources for the current JDBC ResultSet object are released, and an SQLException is thrown. Subsequent calls to getNextResultSet return null.

getNextResultSet(int)

Formats:

```
public ResultSet getNextResultSet(int current)
```

After a stored procedure call, returns a result set from the stored procedure.

A null value is returned if any of the following conditions are true:

- There are no more result sets to be returned.
- The stored procedure call did not produce any result sets.

- A stored procedure call has not been executed under the execution context.

If an error occurs during a call to getNextResultSet, resources for the current JDBC ResultSet object are released, and an SQLException is thrown. Subsequent calls to getNextResultSet return null.

Parameters:

current
Indicates what SQLJ does with the currently open result set before it advances to the next result set:

java.sql.Statement.CLOSE_CURRENT_RESULT
Specifies that the current `ResultSet` object is closed when the next `ResultSet` object is returned.

java.sql.Statement.KEEP_CURRENT_RESULT
Specifies that the current `ResultSet` object stays open when the next `ResultSet` object is returned.

java.sql.Statement.CLOSE_ALL_RESULTS
Specifies that all open `ResultSet` objects are closed when the next `ResultSet` object is returned.

getQueryTimeout
Format:

```
public synchronized int getQueryTimeout()
```

Returns the maximum number of seconds that SQL operations that use the given execution context object can execute. If an SQL operation exceeds the limit, an SQLException is thrown. The returned value is the value that was set by the setQueryTimeout method, or 0 if no value was set by setQueryTimeout. 0 means that execution time is unlimited.

getUpdateCount
Format:

```
public abstract int getUpdateCount() throws SQLException
```

Returns:

ExecutionContext.ADD_BATCH_COUNT
If the statement was added to an existing batch.

ExecutionContext.NEW_BATCH_COUNT
If the statement was the first statement in a new batch.

ExecutionContext.EXCEPTION_COUNT
If the previous statement generated an SQLException, or no previous statement was executed.

ExecutionContext.EXEC_BATCH_COUNT
If the statement was part of a batch, and the batch was executed.

ExecutionContext.QUERY_COUNT
If the previous statement created an iterator object or JDBC ResultSet.

Other integer
If the statement was executed rather than added to a batch. This value is the number of rows that were updated by the statement.

getWarnings
Format:

```
public synchronized SQLWarning getWarnings()
```

Returns the first warning that was reported by the last SQL operation that was executed using the given execution context. Subsequent warnings are chained to the first warning. If no warnings occurred, null is returned.

getWarnings is used to retrieve positive SQLCODEs.

isBatching
Format:

```
public synchronized boolean isBatching()
```

Returns `true` if batching is enabled for the execution context. Returns `false` if batching is disabled.

registerStatement
Format:

```
public RTStatement registerStatement(ConnectionContext connCtx,
 Object profileKey, int stmtNdx)
 throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

releaseStatement
Format:

```
public void releaseStatement() throws SQLException
```

This method is used by code that is generated by the SQLJ translator. It is not intended for direct use by application programs.

setBatching
Format:

```
public synchronized void setBatching(boolean batching)
```

Parameters:

batching
Indicates whether batchable statements that are registered with the given execution context can be added to a statement batch:

`true`
Statements can be added to a statement batch.

`false`
Statements are executed individually.

setBatching affects only statements that occur in the program after setBatching is called. It does not affect previous statements or an existing statement batch.

setBatchLimit
Format:

```
public synchronized void setBatchLimit(int batch-size)
```

Sets the maximum number of statements that are added to a batch before the batch is implicitly executed.

Parameters:

batch-size
One of the following values:

`ExecutionContext.UNLIMITED_BATCH`
Indicates that implicit execution occurs only when SQLJ encounters a statement that is batchable but incompatible, or not batchable. Setting this value is the same as not invoking `setBatchLimit`.

ExecutionContext.AUTO_BATCH
Indicates that implicit execution occurs when the number of statements in the batch reaches a number that is set by SQLJ.

Positive integer
The number of statements that are added to the batch before SQLJ executes the batch implicitly. The batch might be executed before this many statements have been added if SQLJ encounters a statement that is batchable but incompatible, or not batchable.

setBatchLimit affects only statements that occur in the program after setBatchLimit is called. It does not affect an existing statement batch.

setFetchDirection
Format:

```
public synchronized void setFetchDirection(int direction) throws SQLException
```

Gives SQLJ a hint as to the current fetch direction for scrollable iterator objects that were generated from the given execution context.

Parameters:

direction
One of the following values:

sqlj.runtime.ResultSetIterator.FETCH_FORWARD
Rows are fetched in a forward direction. This is the default.

sqlj.runtime.ResultSetIterator.FETCH_REVERSE
Rows are fetched in a backward direction.

sqlj.runtime.ResultSetIterator.FETCH_UNKNOWN
The order of fetching is unknown.

Any other input value results in an SQLException.

setFetchSize
Format:

```
synchronized public void setFetchSize(int number-of-rows) throws SQLException
```

Gives SQLJ a hint as to the number of rows that should be fetched when more rows are needed.

Parameters:

number-of-rows
The expected number of rows that SQLJ should fetch for the iterator that is associated with the given execution context.

If *number-of-rows* is less than 0 or greater than the maximum number of rows that can be fetched, an SQLException is thrown.

setMaxFieldSize
Format:

```
public void setMaxFieldSize(int max-bytes)
```

Specifies the maximum number of bytes that are returned for any string (character, graphic, or varying-length binary) column in queries that use the given execution context. If this limit is exceeded, SQLJ discards the remaining bytes.

Parameters:

max-bytes
The maximum number of bytes that SQLJ should return from a BINARY, VARBINARY, CHAR, VARCHAR, GRAPHIC, or VARGRAPHIC column. A value of 0 means that the number of bytes is unlimited. 0 is the default.

setMaxRows

Format:

```
public synchronized void setMaxRows(int max-rows)
```

Specifies the maximum number of rows that are returned for any query that uses the given execution context. If this limit is exceeded, SQLJ discards the remaining rows.

When `setMaxRows` is invoked at run time on a statically executed SELECT statement, `setMaxRows` limits the maximum number of rows in the result table through IBM Data Server Driver for JDBC and SQLJ processing only. Data server optimization that limits the number of rows in the result table does not occur unless the FETCH FIRST *n* ROWS ONLY clause is also added to the SELECT statement. If FETCH FIRST *n* rows ONLY is added to the SELECT statement, and setMaxRows(*m*) is called, the maximum number of rows is the smaller of *n* and *m*. The driver discards the rest of the rows.

Parameters:

max-rows
The maximum number of rows that SQLJ should return for a query that uses the given execution context. A value of 0 means that the number of rows is unlimited. 0 is the default.

setQueryTimeout

Format:

```
public synchronized void setQueryTimeout(int timeout-value)
```

Specifies the maximum number of seconds that SQL operations that use the given execution context object can execute. If an SQL operation exceeds the limit, an SQLException is thrown.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS data servers, `setQueryTimeout` is supported only if `Connection` or `DataSource` property queryTimeoutInterruptProcessingMode is set to INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET.

Parameters:

timeout-value
The maximum number of seconds that SQL operations that use the given execution context object can execute. 0 means that execution time is unlimited. 0 is the default.

Related tasks

"Controlling the execution of SQL statements in SQLJ" on page 158
You can use selected methods of the SQLJ `ExecutionContext` class to control or monitor the execution of SQL statements.

sqlj.runtime.SQLNullException class

The `sqlj.runtime.SQLNullException` class is derived from the `java.sql.SQLException` class.

An `sqlj.runtime.SQLNullException` is thrown when an SQL NULL value is fetched into a host identifier with a Java primitive type. The SQLSTATE value for an instance of `SQLNullException` is '22002'.

sqlj.runtime.StreamWrapper class

The `sqlj.runtime.StreamWrapper` class wraps a `java.io.InputStream` instance and extends the `java.io.InputStream` class.

The `sqlj.runtime.AsciiStream`, `sqlj.runtime.BinaryStream`, and `sqlj.runtime.UnicodeStream` classes extend `sqlj.runtime.StreamWrapper`. `sqlj.runtime.StreamWrapper` supports methods for specifying the length of `sqlj.runtime.AsciiStream`, `sqlj.runtime.BinaryStream`, and `sqlj.runtime.UnicodeStream` objects.

Constructors

StreamWrapper(InputStream)

Format:

```
protected StreamWrapper(InputStream input-stream)
```

Creates an `sqlj.runtime.StreamWrapper` object with an unspecified length.

Parameters:

input-stream
The `InputStream` object that the `sqlj.runtime.StreamWrapper` object wraps.

StreamWrapper(InputStream, int)

Format:

```
protected StreamWrapper(java.io.InputStream input-stream, int length)
```

Creates an `sqlj.runtime.StreamWrapper` object with a specified length.

Parameters:

input-stream
The `InputStream` object that the `sqlj.runtime.StreamWrapper` object wraps.

length
The length of the `InputStream` object in bytes.

Methods

getInputStream

Format:

```
public InputStream getInputStream()
```

Returns the underlying `InputStream` object that is wrapped by the `StreamWrapper` object.

getLength

Format:

```
public void getLength()
```

Returns the length in bytes of the wrapped `InputStream` object, as specified by the constructor or in the last call to setLength.

setLength

Format:

```
public void setLength (int length)
```

Sets the number of bytes that are read from the wrapped `InputStream` object when the object is passed as an input argument to an SQL operation.

Parameters:

length
The number of bytes that are read from the wrapped `InputStream` object.

Related reference

“sqlj.runtime.UnicodeStream class” on page 387
The `sqlj.runtime.UnicodeStream` class is for an input stream of Unicode data with a specified length.

“sqlj.runtime.CharacterStream class” on page 376

The `sqlj.runtime.CharacterStream` class is for an input stream of character data with a specified length.

"sqlj.runtime.BinaryStream class" on page 376
The `sqlj.runtime.BinaryStream` class is for an input stream of binary data with a specified length.

"sqlj.runtime.AsciiStream class" on page 375
The `sqlj.runtime.AsciiStream` class is for an input stream of ASCII data with a specified length.

sqlj.runtime.UnicodeStream class

The `sqlj.runtime.UnicodeStream` class is for an input stream of Unicode data with a specified length.

The `sqlj.runtime.UnicodeStream` class is derived from the java.io.InputStream class, and extends the `sqlj.runtime.StreamWrapper` class. SQLJ interprets the bytes in an `sqlj.runtime.UnicodeStream` object as Unicode characters. An InputStream object with Unicode characters needs to be passed as a `sqlj.runtime.UnicodeStream` object.

Constructors

UnicodeStream(InputStream)

Format:

```
public UnicodeStream(java.io.InputStream input-stream)
```

Creates a Unicode `java.io.InputStream` object with an unspecified length.

Parameters:

input-stream
The `InputStream` object that SQLJ interprets as an `UnicodeStream` object.

UnicodeStream(InputStream, int)

Format:

```
public UnicodeStream(java.io.InputStream input-stream, int length)
```

Creates a Unicode `java.io.InputStream` object with a specified length.

Parameters:

input-stream
The `InputStream` object that SQLJ interprets as an `UnicodeStream` object.

length
The length of the `InputStream` object that SQLJ interprets as an `UnicodeStream` object.

Related reference

"sqlj.runtime.StreamWrapper class" on page 385
The `sqlj.runtime.StreamWrapper` class wraps a `java.io.InputStream` instance and extends the `java.io.InputStream` class.

"sqlj.runtime.CharacterStream class" on page 376
The `sqlj.runtime.CharacterStream` class is for an input stream of character data with a specified length.

"sqlj.runtime.BinaryStream class" on page 376
The `sqlj.runtime.BinaryStream` class is for an input stream of binary data with a specified length.

"sqlj.runtime.AsciiStream class" on page 375

The `sqlj.runtime.AsciiStream` class is for an input stream of ASCII data with a specified length.

IBM Data Server Driver for JDBC and SQLJ extensions to JDBC

The IBM Data Server Driver for JDBC and SQLJ provides a set of extensions to the support that is provided by the JDBC specification.

To use IBM Data Server Driver for JDBC and SQLJ-only methods in classes that have corresponding, standard classes, cast an instance of the related, standard JDBC class to an instance of the IBM Data Server Driver for JDBC and SQLJ-only class. For example:

```
javax.sql.DataSource ds =
 new com.ibm.db2.jcc.DB2SimpleDataSource();
((com.ibm.db2.jcc.DB2BaseDataSource) ds).setServerName("sysmvs1.stl.ibm.com");
```

Table 95 on page 388 summarizes the IBM Data Server Driver for JDBC and SQLJ-only interfaces.

Table 95. Summary of IBM Data Server Driver for JDBC and SQLJ-only interfaces provided by the IBM Data Server Driver for JDBC and SQLJ

Interface name	Applicable data sources	Purpose
DB2CallableStatement	"1" on page 389, "2" on page 389	Extends the `java.sql.CallableStatement` and the `com.ibm.db2.jcc.DB2PreparedStatement` interfaces.
DB2Connection	"1" on page 389, "2" on page 389, "3" on page 389	Extends the `java.sql.Connection` interface.
DB2DatabaseMetaData	"1" on page 389, "2" on page 389, "3" on page 389	Extends the `java.sql.DatabaseMetaData` interface.
DB2Diagnosable	"1" on page 389, "2" on page 389, "3" on page 389	Provides a mechanism for getting Db2 diagnostics from a Db2 `SQLException`.
DB2JSONResultSet	"1" on page 389, "2" on page 389, "3" on page 389	Used for converting the contents of JDBC `ResultSet` objects to JSON documents and snippets.
DB2ParameterMetaData	"2" on page 389	Extends the `java.sql.ParameterMetaData` interface.
DB2PreparedStatement	"1" on page 389, "2" on page 389, "3" on page 389	Extends the `com.ibm.db2.jcc.DB2Statement` and `java.sql.PreparedStatement` interfaces.
DB2ResultSet	"1" on page 389, "2" on page 389, "3" on page 389	Extends the `java.sql.ResultSet` interface.
DB2RowID	"1" on page 389, "2" on page 389	Used for declaring Java objects for use with the ROWID data type.
DB2Statement	"1" on page 389, "2" on page 389, "3" on page 389	Extends the `java.sql.Statement` interface.
DB2Struct	"2" on page 389	Provides methods for working with `java.sql.Struct` objects.
DB2SystemMonitor	"1" on page 389, "2" on page 389, "3" on page 389	Used for collecting system monitoring data for a connection.
DB2TraceManagerMXBean	"1" on page 389, "2" on page 389, "3" on page 389	Provides the MBean interface for the remote trace controller.

Table 95. Summary of IBM Data Server Driver for JDBC and SQLJ-only interfaces provided by the IBM Data Server Driver for JDBC and SQLJ (continued)

Interface name	Applicable data sources	Purpose
DB2Xml	"1" on page 389, "2" on page 389	Used for updating data in XML columns and retrieving data from XML columns.
DBBatchUpdateException	"1" on page 389, "2" on page 389, "3" on page 389	Used for retrieving error information about batch execution of statements that return automatically generated keys.

Note: The interface applies to connections to the following data sources:

1. Db2 for z/OS
2. Db2 on Linux, UNIX, and Windows systems
3. IBM Informix

Table 96 on page 389 summarizes the IBM Data Server Driver for JDBC and SQLJ-only classes.

Table 96. Summary of IBM Data Server Driver for JDBC and SQLJ-only classes provided by the IBM Data Server Driver for JDBC and SQLJ

Class name	Applicable data sources	Purpose
DB2Administrator	"2" on page 391	Instances of the `DB2Administrator` class are used to retrieve `DB2CataloguedDatabase` objects.
DB2BaseDataSource	"1" on page 391, "2" on page 391, "3" on page 391	The abstract data source parent class for all IBM Data Server Driver for JDBC and SQLJ-specific implementations of `javax.sql.DataSource`, `javax.sql.ConnectionPoolDataSource`, and `javax.sql.XADataSource`.
DB2Binder	"1" on page 391, "2" on page 391	Provides the runJDBCBinder method as an alternative to the DB2Binder utility for binding IBM Data Server Driver for JDBC and SQLJ packages.
DB2BlobFileReference	"1" on page 391	A subclass of `DB2FileReference` for creating BLOB file reference variable objects.
DB2CataloguedDatabase	"2" on page 391	Contains methods that retrieve information about a local Db2 on Linux, UNIX, and Windows systems database.
DB2ClientRerouteServerList	"1" on page 391, "2" on page 391	Implements the `java.io.Serializable` and `javax.naming.Referenceable` interfaces.
DB2ClobFileReference	"1" on page 391	A subclass of `DB2FileReference` for creating CLOB file reference variable objects.
DB2ConnectionPool	"1" on page 391, "2" on page 391	Provides constructors, methods, and properties for managing connection pooling.
DB2ConnectionPoolDataSource	"1" on page 391, "2" on page 391, "3" on page 391	A factory for `PooledConnection` objects.

Table 96. Summary of IBM Data Server Driver for JDBC and SQLJ-only classes provided by the IBM Data Server Driver for JDBC and SQLJ (continued)

Class name	Applicable data sources	Purpose
DB2DataSource	"1" on page 391, "2" on page 391, "3" on page 391	Extends the extends `DB2BaseDataSource` class, and implements the `javax.sql.DataSource`, `java.io.Serializable`, and `javax.naming.Referenceable` interfaces.
DB2Driver	"1" on page 391, "2" on page 391, "3" on page 391	Extends the `java.sql.Driver` interface.
DB2ExceptionFormatter	"1" on page 391, "2" on page 391, "3" on page 391	Contains methods for printing diagnostic information to a stream.
DB2FileReference	"1" on page 391	Provides methods for inserting data into tables from file reference variables.
DB2JCCPlugin	"2" on page 391	The abstract class for implementation of JDBC security plug-ins.
DB2PooledConnection	"1" on page 391, "2" on page 391, "3" on page 391	Provides methods that an application server can use to switch users on a preexisting trusted connection.
DB2PoolMonitor	"1" on page 391, "2" on page 391	Provides methods for monitoring the global transport objects pool for the connection concentrator and sysplex workload balancing.
DB2SimpleDataSource	"1" on page 391, "2" on page 391, "3" on page 391	Extends the `DataBaseDataSource` class. Does not support connection pooling or distributed transactions.
DB2Sqlca	"1" on page 391, "2" on page 391, "3" on page 391	An encapsulation of the Db2 SQLCA.
DB2TraceManager	"1" on page 391, "2" on page 391, "3" on page 391	Controls the global log writer.
DB2Types	"1" on page 389	Defines data type constants.
DB2Version	"1" on page 391, "2" on page 391, "3" on page 391	Provides methods that return information about the IBM Data Server Driver for JDBC and SQLJ version.
DB2XADataSource	"1" on page 391, "2" on page 391, "3" on page 391	A factory for `XADataSource` objects. An object that implements this interface is registered with a naming service that is based on the Java Naming and Directory Interface (JNDI).
DB2XmlAsBlobFileReference	"1" on page 391	A subclass of `DB2FileReference` for creating XML AS BLOB file reference variable objects.
DB2XmlAsClobFileReference	"1" on page 391	A subclass of `DB2FileReference` for creating XML AS CLOB file reference variable objects.
DBTimestamp	"1" on page 391, "2" on page 391, "3" on page 391	A subclass of `Timestamp` that handles timestamp values with extra precision or time zone information.
LoadResult	"1" on page 391	Provides methods for returning the results of a `DB2Connection.zLoad` invocation.

Table 96. Summary of IBM Data Server Driver for JDBC and SQLJ-only classes provided by the IBM Data Server Driver for JDBC and SQLJ (continued)

Class name	Applicable data sources	Purpose

Note: The class applies to connections to the following data sources:

1. Db2 for z/OS
2. Db2 on Linux, UNIX, and Windows systems
3. IBM Informix

DBBatchUpdateException interface

The `com.ibm.db2.jcc.DBBatchUpdateException` interface is used for retrieving error information about batch execution of statements that return automatically generated keys.

DBBatchUpdateException methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getDBGeneratedKeys

Format:

```
public java.sql.ResultSet[] getDBGeneratedKeys()
  throws java.sql.SQLException
```

Retrieves automatically generated keys that were created when INSERT statements were executed in a batch. Each `ResultSet` object that is returned contains the automatically generated keys for a single statement in the batch. `ResultSet` objects that are null correspond to failed statements.

DB2BaseDataSource class

The `com.ibm.db2.jcc.DB2BaseDataSource` class is the abstract data source parent class for all IBM Data Server Driver for JDBC and SQLJ-specific implementations of `javax.sql.DataSource`, `javax.sql.ConnectionPoolDataSource`, and `javax.sql.XADataSource`.

The `DB2BaseDataSource` properties implement the `java.sql.Wrapper` interface.

DB2BaseDataSource properties

The following properties are defined only for the IBM Data Server Driver for JDBC and SQLJ.

You can set all properties on a `DataSource` or in the *url* parameter in a `DriverManager.getConnection` call.

All properties **except** the following properties have a `setXXX` method to set the value of the property and a `getXXX` method to retrieve the value:

- dumpPool
- dumpPoolStatisticsOnSchedule
- dumpPoolStatisticsOnScheduleFile
- maxTransportObjectIdleTime
- maxTransportObjectWaitTime
- minTransportObjects
- xmlFormat

A `setXXX` method has this form:

```
void setProperty-name(data-type property-value)
```

A getXXX method has this form:

```
data-type getProperty-name()
```

The *Property-name* property is the unqualified property name. For properties that are not specific to IBM Informix, the first character of the property name is capitalized. For properties that are used only by IBM Informix, all characters of the property name are capitalized.

The following table lists the IBM Data Server Driver for JDBC and SQLJ properties and their data types.

Table 97. DB2BaseDataSource properties and their data types

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.accessToken (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"3" on page 399	String	4.24
com.ibm.db2.jcc.DB2BaseDataSource.accountingInterval	"2" on page 399	String	3.6
com.ibm.db2.jcc.DB2BaseDataSource.alternateGroupDatabaseName	"3" on page 399	String	3.66, 4.16
com.ibm.db2.jcc.DB2BaseDataSource.alternateGroupPortNumber	"3" on page 399	String	3.66, 4.16
com.ibm.db2.jcc.DB2BaseDataSource.alternateGroupServerName	"3" on page 399	String	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.affinityFailbackInterval	"1" on page 399	int	3.58, 4.8
com.ibm.db2.jcc.DB2BaseDataSource.allowNextOnExhaustedResultSet	"1" on page 399	int	3.51, 4.1
com.ibm.db2.jcc.DB2BaseDataSource.allowNullResultSetForExecuteQuery	"1" on page 399	int	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.apiKey IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"3" on page 399	String	4.24
com.ibm.db2.jcc.DB2BaseDataSource.atomicMultiRowInsert	"1" on page 399	int	3.57, 4.7
com.ibm.db2.jcc.DB2BaseDataSource.blockingReadConnectionTimeout	"1" on page 399	int	2.8
com.ibm.db2.jcc.DB2BaseDataSource.charOutputSize	"2" on page 399	short	2.10
com.ibm.db2.jcc.DB2BaseDataSource.clientAccountingInformation	"2" on page 399, "3" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.clientApplcompat (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399	String	3.72, 4.22
com.ibm.db2.jcc.DB2BaseDataSource.clientApplicationInformation	"2" on page 399, "3" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.clientDebugInfo (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399, "3" on page 399	String	3.0
com.ibm.db2.jcc.DB2BaseDataSource.clientProgramId	"2" on page 399, "3" on page 399	String	2.3
com.ibm.db2.jcc.DB2BaseDataSource.clientProgramName (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399, "3" on page 399	String	2.2
com.ibm.db2.jcc.DB2BaseDataSource.clientRerouteAlternateServerName	"1" on page 399	String	3.4
com.ibm.db2.jcc.DB2BaseDataSource.clientRerouteAlternatePortNumber	"1" on page 399	String	3.4

Table 97. DB2BaseDataSource properties and their data types (continued)

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.clientRerouteServerListJNDIContext	"1" on page 399	javax.naming.Context	3.3
com.ibm.db2.jcc.DB2BaseDataSource.clientRerouteServerListJNDIName	"1" on page 399	String	2.1
com.ibm.db2.jcc.DB2BaseDataSource.clientUser (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"2" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.clientWorkstation (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"2" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.commandTimeout (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	int	3.64, 4.14
com.ibm.db2.jcc.DB2BaseDataSource.connectionCloseWithInFlightTransaction	"1" on page 399	String	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.concurrentAccessResolution	"2" on page 399, "3" on page 399	int	3.53, 4.3
com.ibm.db2.jcc.DB2BaseDataSource.connectNode	"3" on page 399	int	3.4
com.ibm.db2.jcc.DB2BaseDataSource.connectionTimeout (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	int	3.64, 4.14
com.ibm.db2.jcc.DB2BaseDataSource.currentDegree	"2" on page 399, "3" on page 399	String	3.0
com.ibm.db2.jcc.DB2BaseDataSource.currentExplainMode	"2" on page 399, "3" on page 399	String	2.6
com.ibm.db2.jcc.DB2BaseDataSource.currentExplainSnapshot	"3" on page 399	String	2.6
com.ibm.db2.jcc.DB2BaseDataSource.currentFunctionPath	"2" on page 399, "3" on page 399	String	1.3
com.ibm.db2.jcc.DB2BaseDataSource.currentLocaleLcCtype	"2" on page 399	String	3.64, 4.14
com.ibm.db2.jcc.DB2BaseDataSource.currentLockTimeout	"3" on page 399, "4" on page 399	int	2.2
com.ibm.db2.jcc.DB2BaseDataSource.currentMaintainedTableTypesForOptimization	"2" on page 399, "3" on page 399	String	2.2
com.ibm.db2.jcc.DB2BaseDataSource.currentPackagePath	"2" on page 399, "3" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.currentPackageSet	"2" on page 399, "3" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.currentQueryOptimization	"3" on page 399	int	2.2
com.ibm.db2.jcc.DB2BaseDataSource.currentRefreshAge	"2" on page 399, "3" on page 399	long	2.2
com.ibm.db2.jcc.DB2BaseDataSource.currentSchema	"2" on page 399, "3" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.cursorSensitivity	"2" on page 399, "3" on page 399	int	1.5
com.ibm.db2.jcc.DB2BaseDataSource.currentSQLID	"2" on page 399	String	1.3

Table 97. DB2BaseDataSource properties and their data types (continued)

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.databaseName	"1" on page 399	String	1.0
com.ibm.db2.jcc.DB2BaseDataSource.dateFormat	"2" on page 399, "3" on page 399	int	3.3
com.ibm.db2.jcc.DB2BaseDataSource.decimalRoundingMode	"2" on page 399, "3" on page 399	int	3.4
com.ibm.db2.jcc.DB2BaseDataSource.decimalSeparator	"1" on page 399	int	3.53, 4.3
com.ibm.db2.jcc.DB2BaseDataSource.decimalStringFormat	"1" on page 399	int	3.8
com.ibm.db2.jcc.DB2BaseDataSource.defaultIsolationLevel	"1" on page 399	int	3.4
com.ibm.db2.jcc.DB2BaseDataSource.deferPrepares	"1" on page 399	Boolean	1.0
com.ibm.db2.jcc.DB2BaseDataSource.description	"1" on page 399	String	1.0
com.ibm.db2.jcc.DB2BaseDataSource.downgradeHoldCursorsUnderXa	"1" on page 399	Boolean	3.3
com.ibm.db2.jcc.DB2BaseDataSource.driverType	"1" on page 399	int	1.0
com.ibm.db2.jcc.DB2BaseDataSource.dumpPool	"4" on page 399	int	3.52, 4.2
com.ibm.db2.jcc.DB2BaseDataSource.dumpPoolStatisticsOnSchedule	"4" on page 399	int	3.52, 4.2
com.ibm.db2.jcc.DB2BaseDataSource.dumpPoolStatisticsOnScheduleFile	"4" on page 399	String	3.52, 4.2
com.ibm.db2.jcc.DB2BaseDataSource.enableAlternateGroupSeamlessACR	"3" on page 399	Boolean	3.66, 4.16
com.ibm.db2.jcc.DB2BaseDataSource.enableClientAffinitiesList	"1" on page 399	int	3.51, 4.1
com.ibm.db2.jcc.DB2BaseDataSource.enableDualTransportUsingDifferentProcess	"3" on page 399	int	4.31
com.ibm.db2.jcc.DB2BaseDataSource.enableExtendedIndicators	"2" on page 399, "3" on page 399	int	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.enableNamedParameterMarkers	"1" on page 399	int	3.57, 4.7
com.ibm.db2.jcc.DB2BaseDataSource.enableConnectionConcentrator (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399, "4" on page 399	Boolean	2.6
com.ibm.db2.jcc.DB2BaseDataSource.enableMultiRowInsertSupport	"2" on page 399	Boolean	3.58, 4.8
com.ibm.db2.jcc.DB2BaseDataSource.enableRowsetSupport	"2" on page 399, "3" on page 399	int	3.7
com.ibm.db2.jcc.DB2BaseDataSource.enableSeamlessFailover	"1" on page 399	int	3.51, 4.1
com.ibm.db2.jcc.DB2BaseDataSource.enableSeamlessFailoverErrorCodes (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399	Boolean	4.32
com.ibm.db2.jcc.DB2BaseDataSource.enableSysplexWLB (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	Boolean	2.6

Table 97. DB2BaseDataSource properties and their data types (continued)

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.encryptionAlgorithm	"2" on page 399, "3" on page 399	int	2.11
com.ibm.db2.jcc.DB2BaseDataSource.enableExtendedDescribe	"2" on page 399, "3" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.enableT2zosLBF (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"2" on page 399	int	3.61, 4.11
com.ibm.db2.jcc.DB2BaseDataSource.enableT2zosLBFSPResultSets (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"2" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.enableTimeoutOnCursor	"2" on page 399, "3" on page 399	int	3.67, 4.17
com.ibm.db2.jcc.DB2BaseDataSource.extendedTableInfo	"2" on page 399	int	3.68, 4.18
com.ibm.db2.jcc.DB2BaseDataSource.fetchSize	"1" on page 399	int	3.53, 4.3
com.ibm.db2.jcc.DB2BaseDataSource.floatingPointStringFormat	"1" on page 399	int	3.58, 4.8
com.ibm.db2.jcc.DB2BaseDataSource.fullyMaterializeInputStreams	"2" on page 399, "3" on page 399	Boolean	2.7
com.ibm.db2.jcc.DB2BaseDataSource.fullyMaterializeLobData	"1" on page 399	Boolean	1.0
com.ibm.db2.jcc.DB2BaseDataSource.gssCredential	"2" on page 399, "3" on page 399	Object	1.0
com.ibm.db2.jcc.DB2BaseDataSource.implicitRollbackOption	"1" on page 399	int	3.64, 4.14
com.ibm.db2.jcc.DB2BaseDataSource.interruptProcessingMode (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	int	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.jdbcCollection	"2" on page 399	String	1.2
com.ibm.db2.jcc.DB2BaseDataSource.keepAliveTimeOut (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.keepDynamic	"2" on page 399, "4" on page 399	int	1.5
com.ibm.db2.jcc.DB2BaseDataSource.kerberosServerPrincipal	"2" on page 399, "3" on page 399	String	1.1
com.ibm.db2.jcc.DB2BaseDataSource.keyUsage (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399	int	4.23
com.ibm.db2.jcc.DB2BaseDataSource.loginTimeout (not supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"1" on page 399	int	1.4
com.ibm.db2.jcc.DB2BaseDataSource.logWriter	"1" on page 399	PrintWriter	1.0
com.ibm.db2.jcc.DB2BaseDataSource.maxConnCachedParamBufferSize (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"2" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.maxRetriesForClientReroute	"3" on page 399, "4" on page 399	int	2.7
com.ibm.db2.jcc.DB2BaseDataSource.maxStatements	"1" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.maxRowsetSize (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"2" on page 399	int	3.7

Table 97. DB2BaseDataSource properties and their data types (continued)

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.maxTransportObjectIdleTime	"4" on page 399	int	3.52, 4.2
com.ibm.db2.jcc.DB2BaseDataSource.maxTransportObjectWaitTime	"1" on page 399	int	3.52, 4.2
com.ibm.db2.jcc.DB2BaseDataSource.maxTransportObjects	"2" on page 399, "4" on page 399	int	2.6
com.ibm.db2.jcc.DB2BaseDataSource.MAXBLKEXT (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399, "3" on page 399	int	4.32
com.ibm.db2.jcc.DB2BaseDataSource.memberConnectTimeout (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"3" on page 399, "4" on page 399	int	3.65, 4.15
com.ibm.db2.jcc.DB2BaseDataSource.minTransportObjects	"4" on page 399	int	3.52, 4.2
com.ibm.db2.jcc.DB2BaseDataSource.optimizationProfile	"3" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.optimizationProfileToFlush	"3" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.password	"1" on page 399	String	1.0
com.ibm.db2.jcc.DB2BaseDataSource.pdqProperties	"2" on page 399, "3" on page 399	String	3.52, 4.2
com.ibm.db2.jcc.DB2BaseDataSource.pkList (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity only)	"2" on page 399	String	1.4
com.ibm.db2.jcc.DB2BaseDataSource.planName (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity only)	"2" on page 399	String	1.4
com.ibm.db2.jcc.DB2BaseDataSource.plugin	"3" on page 399	Object	2.8
com.ibm.db2.jcc.DB2BaseDataSource.pluginName	"3" on page 399	String	2.8
com.ibm.db2.jcc.DB2BaseDataSource.portNumber	"1" on page 399	int	1.0
com.ibm.db2.jcc.DB2BaseDataSource.progressiveStreaming	"1" on page 399	int	3.0
com.ibm.db2.jcc.DB2BaseDataSource.queryCloseImplicit	"1" on page 399	int	3.0
com.ibm.db2.jcc.DB2BaseDataSource.queryDataSize	"1" on page 399	int	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.queryPrefetch (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399, "3" on page 399	Boolean	4.29
com.ibm.db2.jcc.DB2BaseDataSource.queryTimeoutInterruptProcessingMode (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 on Linux, UNIX, and Windows systems or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	int	3.62, 4.12
com.ibm.db2.jcc.DB2BaseDataSource.readOnly	"2" on page 399, "3" on page 399	Boolean	1.0
com.ibm.db2.jcc.DB2BaseDataSource.reportLongTypes	"2" on page 399	short	3.6
com.ibm.db2.jcc.DB2BaseDataSource.resultSetHoldability	"1" on page 399	int	1.0
com.ibm.db2.jcc.DB2BaseDataSource.resultSetHoldabilityForCatalogQueries	"2" on page 399, "3" on page 399	int	3.50, 4.0

Table 97. DB2BaseDataSource properties and their data types (continued)

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.retrieveMessagesFromServerOnGetMessage	"1" on page 399	Boolean	1.1
com.ibm.db2.jcc.DB2BaseDataSource.retryIntervalForClientReroute	"3" on page 399, "4" on page 399	int	2.7
com.ibm.db2.jcc.DB2BaseDataSource.retryWithAlternativeSecurityMechanism (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"3" on page 399	int	3.6
com.ibm.db2.jcc.DB2BaseDataSource.returnAlias	"2" on page 399, "3" on page 399	short	2.5
com.ibm.db2.jcc.DB2BaseDataSource.securityMechanism	"1" on page 399	int	1.0
com.ibm.db2.jcc.DB2BaseDataSource.sendCharInputsUTF8	"2" on page 399	int	3.2
com.ibm.db2.jcc.DB2BaseDataSource.sendDataAsIs	"1" on page 399	Boolean	3.0
com.ibm.db2.jcc.DB2BaseDataSource.serverName	"1" on page 399	String	1.0
com.ibm.db2.jcc.DB2BaseDataSource.sessionTimeZone	"2" on page 399	String	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.sqljAvoidTimeStampConversion	"2" on page 399	Boolean	3.69, 4.19
com.ibm.db2.jcc.DB2BaseDataSource.sqljEnableClassLoaderSpecificProfiles	"2" on page 399	Boolean	2.10
com.ibm.db2.jcc.DB2BaseDataSource.ssid (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only)	"2" on page 399	String	3.6
com.ibm.db2.jcc.DB2BaseDataSource.sslCertLocation (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	String	3.69, 4.19
com.ibm.db2.jcc.DB2BaseDataSource.sslCipherSuites (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399	String	3.71, 4.21
com.ibm.db2.jcc.DB2BaseDataSource.sslConnection (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	Boolean	3.0
com.ibm.db2.jcc.DB2BaseDataSource.sslKeyStoreLocation (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399	String	4.23
com.ibm.db2.jcc.DB2BaseDataSource.sslKeyStorePassword (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399	String	4.23
com.ibm.db2.jcc.DB2BaseDataSource.sslKeyStoreType (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399	String	4.23
com.ibm.db2.jcc.DB2BaseDataSource.sslTrustStoreLocation (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	String	3.53, 4.3
com.ibm.db2.jcc.DB2BaseDataSource.sslTrustStorePassword (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	String	3.53, 4.3
com.ibm.db2.jcc.DB2BaseDataSource.sslTrustStoreType (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	String	3.71, 4.21
com.ibm.db2.jcc.DB2BaseDataSource.sslClientHostnameValidation (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"2" on page 399, "3" on page 399	String	4.29
com.ibm.db2.jcc.DB2BaseDataSource.sslVersion (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only)	"1" on page 399	int	4.23
com.ibm.db2.jcc.DB2BaseDataSource.statementConcentrator	"2" on page 399, "3" on page 399	int	3.57, 4.7
com.ibm.db2.jcc.DB2BaseDataSource.streamBufferSize	"2" on page 399, "3" on page 399	int	3.0

Table 97. DB2BaseDataSource properties and their data types (continued)

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.stripTrailingZerosForDecimalNumbers	"1" on page 399	int	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.supportsAsynchronousXARollback	"2" on page 399, "3" on page 399	int	2.7
com.ibm.db2.jcc.DB2BaseDataSource.sysSchema	"2" on page 399, "3" on page 399	String	2.5
com.ibm.db2.jcc.DB2BaseDataSource.timerLevelForQueryTimeOut	"1" on page 399	int	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.timeFormat	"2" on page 399, "3" on page 399	int	3.3
com.ibm.db2.jcc.DB2BaseDataSource.timestampFormat	"1" on page 399	int	3.6
com.ibm.db2.jcc.DB2BaseDataSource.timestampOutputType	"2" on page 399	int	3.59, 4.9
com.ibm.db2.jcc.DB2BaseDataSource.timestampPrecisionReporting	"1" on page 399	int	3.8
com.ibm.db2.jcc.DB2BaseDataSource.traceDirectory	"1" on page 399	String	1.5
com.ibm.db2.jcc.DB2BaseDataSource.traceFile	"1" on page 399	String	1.1
com.ibm.db2.jcc.DB2BaseDataSource.traceFileAppend	"1" on page 399	Boolean	1.2
com.ibm.db2.jcc.DB2BaseDataSource.traceFileCount	"1" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.traceFileSize	"1" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.traceLevel	"1" on page 399	int	1.0
com.ibm.db2.jcc.DB2BaseDataSource.traceOption	"1" on page 399	int	3.63, 4.13
com.ibm.db2.jcc.DB2BaseDataSource.useCachedCursor	"2" on page 399, "3" on page 399	Boolean	2.2
com.ibm.db2.jcc.DB2BaseDataSource.useClientSideLicenseFirst	"2" on page 399, "3" on page 399, "5" on page 399, "6" on page 399	int	4.29
com.ibm.db2.jcc.DB2BaseDataSource.useJDBC4ColumnNameAndLabelSemantics	"2" on page 399, "3" on page 399	int	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.useJDBC41DefinitionForGetColumns	"1" on page 399	int	4.13
com.ibm.db2.jcc.DB2BaseDataSource.user	"1" on page 399	String	1.0
com.ibm.db2.jcc.DB2BaseDataSource.useIdentityValLocalForAutoGeneratedKeys	"2" on page 399, "3" on page 399	Boolean	3.62, 4.12
com.ibm.db2.jcc.DB2BaseDataSource.useRowsetCursor	"2" on page 399	Boolean	3.1
com.ibm.db2.jcc.DB2BaseDataSource.useTransactionRedirect	"3" on page 399	Boolean	2.6

Table 97. DB2BaseDataSource properties and their data types (continued)

Property name	Applicable data sources	Data type	Introduced in driver version
com.ibm.db2.jcc.DB2BaseDataSource.xaNetworkOptimization	"1" on page 399	Boolean	3.3
com.ibm.db2.jcc.DB2BaseDataSource.xmlFormat	"2" on page 399, "3" on page 399	int	3.53, 4.3
com.ibm.db2.jcc.DB2BaseDataSource.DBANSIWARN	"4" on page 399	Boolean	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.DBDATE	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.DBPATH	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.DBSPACETEMP	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.DBTEMP	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.DBUPSPACE	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.DELIMIDENT	"4" on page 399	Boolean	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.IFX_DIRECTIVES	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.IFX_EXTDIRECTIVES	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.IFX_UPDDESC	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.IFX_XASTDCOMPLIANCE_XAEND	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.INFORMIXOPCACHE	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.INFORMIXSTACKSIZE	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.NODEFDAC	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.OPTCOMPIND	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.OPTOFC	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.PDQPRIORITY	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.PSORT_DBTEMP	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.PSORT_NPROCS	"4" on page 399	String	3.50, 4.0
com.ibm.db2.jcc.DB2BaseDataSource.STMT_CACHE	"4" on page 399	String	3.50, 4.0

Note: The property applies to connections to the following data sources:

1. All data servers
2. Db2 for z/OS
3. Db2 on Linux, UNIX, and Windows systems
4. IBM Informix
5. Db2 for IBM i
6. Db2 on Cloud

DB2BaseDataSource fields

The following constants are defined only for the IBM Data Server Driver for JDBC and SQLJ.

public final static int IMPLICIT_ROLLBACK_OPTION_NOT_SET = 0
A constant for the implicitRollbackOption property. This value indicates that a connection is not closed when a deadlock or timeout occurs. This value causes the same behavior as IMPLICIT_ROLLBACK_OPTION_NOT_CLOSE_CONNECTION.

public final static int IMPLICIT_ROLLBACK_OPTION_NOT_CLOSE_CONNECTION = 1
A constant for the implicitRollbackOption property. This value indicates that a connection is not closed when a deadlock or timeout occurs. The IBM Data Server Driver for JDBC and SQLJ returns the error code that the data server generates for a deadlock or timeout.

public final static int IMPLICIT_ROLLBACK_OPTION_CLOSE_CONNECTION = 2
A constant for the implicitRollbackOption property. This value indicates that a connection is closed when a deadlock or timeout occurs.

public final static int INTERRUPT_PROCESSING_MODE_DISABLED = 0
A constant for the interruptProcessingMode property. This value indicates that interrupt processing is disabled.

public final static int INTERRUPT_PROCESSING_MODE_STATEMENT_CANCEL = 1
A constant for the interruptProcessingMode property. This value indicates that the IBM Data Server Driver for JDBC and SQLJ cancels the currently executing statement when an application runs `Statement.cancel`, if the data server supports interrupt processing. This value is supported on Db2 on Linux, UNIX, and Windows systems only.

public final static int INTERRUPT_PROCESSING_MODE_CLOSE_SOCKET = 2
A constant for the interruptProcessingMode property. This value indicates that the IBM Data Server Driver for JDBC and SQLJ drops the underlying socket and closes the connection when an application executes `Statement.cancel`. This value is supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 on Linux, UNIX, and Windows systems or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

public final static int NOT_SET = 0
The default value for properties.

public final static int YES = 1
The YES value for properties.

public final static int NO = 2
The NO value for properties.

public final static int QUERYTIMEOUT_DISABLED = -1
A constant for the timerLevelForQueryTimeOut property. This value indicates that `Timer` objects for waiting for queries to time out are not created.

public final static int QUERYTIMEOUT_STATEMENT_LEVEL = 1
A constant for the timerLevelForQueryTimeOut property. This value indicates that `Timer` objects for waiting for queries to time out are created at the `Statement` level.

public final static int QUERYTIMEOUT_CONNECTION_LEVEL = 2
A constant for the timerLevelForQueryTimeOut property. This value indicates that `Timer` objects for waiting for queries to time out are created at the `Connection` level.

public final static int TRACE_OPTION_CIRCULAR = 1
A constant for the traceOption property. This value indicates that the IBM Data Server Driver for JDBC and SQLJ uses circular tracing.

DB2BaseDataSource methods

In addition to the `getXXX` and `setXXX` methods for the DB2BaseDataSource properties, the following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getReference
Format:

```
public javax.naming.Reference getReference()
  throws javax.naming.NamingException
```

Retrieves the `Reference` of a `DataSource` object. For an explanation of a `Reference`, see the description of `javax.naming.Referenceable` in the Java Platform Standard Edition documentation.

getSSLCipherSuites

Format:

```
public java.lang.String getSSLCipherSuites()
```

Returns the contents of the sslCipherSuites property.

For more information on SSL cipher suites, see:

- Cipher suite specification (z/OS Communications Server: IP Configuration Guide)
- The information on Java Cryptography Architecture in the Java Platform Standard Edition documentation

setSSLCipherSuites

Format:

```
synchronized public void setSSLCipherSuites(String cipherSuites)
```

Specifies a set of cipher suites that the IBM Data Server Driver for JDBC and SQLJ uses when it negotiates SSL connections.

For more information on SSL cipher suites, see:

- Cipher suite specification (z/OS Communications Server: IP Configuration Guide)
- The information on Java Cryptography Architecture in the Java Platform Standard Edition documentation

Parameters:

cipherSuites
A string that contains the names of cipher suites that are to be enabled. If there is more than one cipher suite name, the names are separated by commas (,).

Related reference

Properties for the IBM Data Server Driver for JDBC and SQLJ
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

DB2Binder class

The `com.ibm.db2.jcc.DB2Binder` class provides the runJDBCBinder method as an alternative to the DB2Binder utility for binding IBM Data Server Driver for JDBC and SQLJ packages.

DB2Binder methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

runJDBCBinder

Format:

```
public void runJDBCBinder(DB2Connection connection,
  java.util.Properties db2BinderOptions)
  throws SQLException
```

Binds a IBM Data Server Driver for JDBC and SQLJ package.

Parameters:

connection
A DB2Connection object for a connection that was established at the data server on which the packages are being bound.

db2BinderOptions
A java.util.Properties object that contains key and value pairs, in which each key is the name of a DB2Binder utility option, and each value is the value to which you want to set that DB2Binder option. See "DB2Binder utility" on page 539 for a list of DB2Binder options.

For example, suppose that con is a previously defined Connection object. Set the property values in the following way.

```
DB2Binder db2binder = new DB2Binder();
Properties prop = new Properties();
prop.put ("action", "replace");
prop.put ("bindoptions", "DEFER(PREPARE) IMMEDWRITE(NO) REOPT(NONE)");
db2binder.runJDBCBinder((DB2Connection)con,prop);
```

This method is not supported for connections to IBM Informix.

DB2BlobFileReference class

The com.ibm.db2.jcc.DB2BlobFileReference class is subclass of DB2FileReference that is used for creating BLOB file reference variable objects. This class applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS Version 9 or later.

DB2BlobFileReference constructor

The following constructor is defined only for the IBM Data Server Driver for JDBC and SQLJ.

DB2BlobFileReference
Format:

```
public DB2BlobFileReference(String fileName)
  throws java.sql.SQLException
```

Constructs a DB2BlobFileReference object for a BLOB file reference variable.

Parameter descriptions:

fileName
The name of the file for the file reference variable. The name must specify the absolute path name for an existing HFS file.

DB2CallableStatement interface

The com.ibm.db2.jcc.DB2CallableStatement interface extends the java.sql.CallableStatement and the com.ibm.db2.jcc.DB2PreparedStatement interfaces.

DB2CallableStatement methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getDBTimestamp
Formats:

```
public DBTimestamp getDBTimestamp(int parameterIndex)
  throws SQLException
public DBTimestamp getDBTimestamp(String parameterName)
  throws SQLException
```

Returns the value of a TIMESTAMP OUT or INOUT parameter as a DBTimestamp object. If the value of the parameter is NULL, the returned value is null.

Parameters:

parameterIndex
The number of the parameter whose value is being retrieved.

parameterName
The name of the parameter whose value is being retrieved.

This method is not supported for connections to IBM Informix.

getJccArrayAtName
Format:

```
public java.sql.Array getJccArrayAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves an ARRAY value that is designated by a named parameter marker as a `java.sql.Array` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccBigDecimalAtName
Format:

```
public java.math.BigDecimal getJccBigDecimalAtName(String parameterMarkerName)
  throws java.sql.SQLException
public java.math.BigDecimal getJccBigDecimalAtName(String parameterMarkerName,
  int scale)
  throws java.sql.SQLException
```

Retrieves a DECIMAL value that is designated by a named parameter marker as a `java.math.BigDecimal` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

scale
The scale of the value that is retrieved.

getJccBlobAtName
Formats:

```
public java.sql.Blob getJccBlobAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a BLOB value that is designated by a named parameter marker as a `java.sql.Blob` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccBooleanAtName
Format:

```
public boolean getJccBooleanAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a BIT or BOOLEAN value that is designated by a named parameter marker as a boolean value.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccByteAtName
Format:

```
public byte getJccByteAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a TINYINT value that is designated by a named parameter marker as a byte value.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccBytesAtName
Format:

```
public byte[] getJccBytesAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a BINARY or VARBINARY value that is designated by a named parameter marker as an array of byte values.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccClobAtName
Format:

```
public java.sql.Blob getJccClobAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a CLOB value that is designated by a named parameter marker as a java.sql.Clob value.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccDateAtName
Formats:

```
public java.sql.Date getJccDateAtName(String parameterMarkerName)
  throws java.sql.SQLException
public java.sql.Date getJccDateAtName(String parameterMarkerName,
  java.util.Calendar cal)
  throws java.sql.SQLException
```

Retrieves a DATE value that is designated by a named parameter marker as a `java.sql.Date` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

cal
The `java.util.Calendar` object that the IBM Data Server Driver for JDBC and SQLJ uses to construct the date.

getJccDoubleAtName
Format:

```
public double getJccDoubleAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a DOUBLE value that is designated by a named parameter marker as a double value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccFloatAtName
Format:

```
public double getJccFloatAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a FLOAT value that is designated by a named parameter marker as a double value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccIntAtName
Format:

```
public int getJccIntAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a INTEGER value that is designated by a named parameter marker as a int value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccLongAtName
Format:

```
public long getJccLongAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a BIGINT value that is designated by a named parameter marker as a long value.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccObjectAtName
Formats:

```
public java.sql.Object getJccObjectAtName(String parameterMarkerName)
  throws java.sql.SQLException
public java.sql.Object getJccObjectAtName(String parameterMarkerName,
  Map map)
  throws java.sql.SQLException
```

Retrieves a value that is designated by a named parameter marker as a `java.sql.Object` value.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

map
The mapping from SQL type names to Java classes.

getJccRowIdAtName
Format:

```
public java.sql.RowId getJccRowIdAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a ROWID value that is designated by a named parameter marker as a `java.sql.RowId` value.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

This method requires the IBM Data Server Driver for JDBC and SQLJ Version 4.8 or later.

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccShortAtName
Format:

```
public short getJccShortAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a SMALLINT value that is designated by a named parameter marker as a short value.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccSQLXMLAtName
Format:

```
public java.sql.SQLXML getJccSQLXMLAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a SQLXML value that is designated by a named parameter marker as a `java.sql.SQLXML` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

This method requires the IBM Data Server Driver for JDBC and SQLJ Version 4.8 or later.

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccStringAtName
Format:

```
public java.lang.String getJccStringAtName(String parameterMarkerName)
  throws java.sql.SQLException
```

Retrieves a CHAR, VARcHAR, or LONGVARCHAR value that is designated by a named parameter marker as a `java.lang.String` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

getJccTimeAtName
Formats:

```
public java.sql.Time getJccTimeAtName(String parameterMarkerName)
  throws java.sql.SQLException
public java.sql.Time getJccTimeAtName(String parameterMarkerName,
  java.util.Calendar cal)
  throws java.sql.SQLException
```

Retrieves a TIME value that is designated by a named parameter marker as a `java.sql.Time` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

cal
The `java.util.Calendar` object that the IBM Data Server Driver for JDBC and SQLJ uses to construct the time.

getJccTimestampAtName
Formats:

```
public java.sql.Timestamp getJccTimestampAtName(String parameterMarkerName)
  throws java.sql.SQLException
public java.sql.Timestamp getJccTimestampAtName(String parameterMarkerName,
  java.util.Calendar cal)
  throws java.sql.SQLException
```

Retrieves a TIMESTAMP value that is designated by a named parameter marker as a `java.sql.Timestamp` value.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for which a value is retrieved.

cal
The `java.util.Calendar` object that the IBM Data Server Driver for JDBC and SQLJ uses to construct the timestamp.

registerJccOutParameterAtName
Formats:

```
public void registerJccOutParameterAtName(String parameterMarkerName,
  int sqlType)
  throws java.sql.SQLException
public void registerJccOutParameterAtName(String parameterMarkerName,
  int sqlType,
  int scale)
  throws java.sql.SQLException
public void registerJccOutParameterAtName(String parameterMarkerName,
  int sqlType,
  String typeName)
  throws java.sql.SQLException
```

Registers an OUT parameter that is identified by *parameterMarkerName* as the JDBC type *sqlType*.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker for the parameter that is to be registered.

sqlType
The JDBC type code, as defined in `java.sql.Types`, of the parameter that is to be registered.

scale
The scale of the parameter that is to be registered. This parameter applies only to this case:

- If *sqlType* is `java.sql.Types.DECIMAL` or `java.sql.Types.NUMERIC`, *scale* is the number of digits to the right of the decimal point.

typeName
If *jdbcType* is `java.sql.Types.DISTINCT` or `java.sql.Types.REF`, the fully-qualified name of the SQL user-defined type of the parameter that is to be registered.

setDBTimestamp
Format:

```
public void setDBTimestamp(String parameterName,
  DBTimestamp timestamp)
  throws java.sql.SQLException
```

Assigns a `DBTimestamp` value to an IN or INOUT parameter.

Parameters:

parameterName
The name of the parameter to which a `DBTimestamp` variable value is assigned.

timestamp
The `DBTimestamp` value that is assigned to the parameter.

This method is not supported for connections to IBM Informix.

`setJccXXXAtName` methods
These methods are inherited from `DB2PreparedStatement`.

DB2ClientRerouteServerList class

The `com.ibm.db2.jcc.DB2ClientRerouteServerList` class implements the `java.io.Serializable` and `javax.naming.Referenceable` interfaces.

DB2ClientRerouteServerList methods

getAlternatePortNumber
Format:

```
public int[] getAlternatePortNumber()
```

Retrieves the port numbers that are associated with the alternate servers.

getAlternateServerName
Format:

```
public String[] getAlternateServerName()
```

Retrieves an array that contains the names of the alternate servers. These values are IP addresses or DNS server names.

getPrimaryPortNumber
Format:

```
public int getPrimaryPortNumber()
```

Retrieves the port number that is associated with the primary server.

getPrimaryServerName
Format:

```
public String[] getPrimaryServerName()
```

Retrieves the name of the primary server. This value is an IP address or a DNS server name.

setAlternatePortNumber
Format:

```
public void setAlternatePortNumber(int[] alternatePortNumberList)
```

Sets the port numbers that are associated with the alternate servers.

setAlternateServerName
Format:

```
public void setAlternateServerName(String[] alternateServer)
```

Sets the alternate server names for servers. These values are IP addresses or DNS server names.

setPrimaryPortNumber
Format:

```
public void setPrimaryPortNumber(int primaryPortNumber)
```

Sets the port number that is associated with the primary server.

setPrimaryServerName
Format:

```
public void setPrimaryServerName(String primaryServer)
```

Sets the primary server name for a server. This value is an IP address or a DNS server name.

Related concepts

"Java client support for high availability on IBM data servers" on page 589
Client applications that connect to Db2 on Linux, UNIX, and Windows systems, Db2 for z/OS, or IBM Informix can easily take advantage of the high availability features of those data servers.

DB2ClobFileReference class

The `com.ibm.db2.jcc.DB2ClobFileReference` class is subclass of `DB2FileReference` that is used for creating CLOB file reference variable objects. This class applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS Version 9 or later.

DB2ClobFileReference constructor

The following constructor is defined only for the IBM Data Server Driver for JDBC and SQLJ.

DB2ClobFileReference

Format:

```
public DB2ClobFileReference(String fileName,
                            int fileCcsid)
  throws java.sql.SQLException
public DB2ClobFileReference(String fileName,
                            String fileEncoding)
  throws java.sql.SQLException
```

Constructs a `DB2ClobFileReference` object for a CLOB file reference variable.

Parameter descriptions:

fileName
The name of the file for the file reference variable. The name must specify the absolute path name for an existing HFS file.

fileCcsid
The CCSID of the data in the file for the file reference variable.

fileEncoding
The encoding scheme of the data in the file for the file reference variable.

DB2Connection interface

The `com.ibm.db2.jcc.DB2Connection` interface extends the `java.sql.Connection` interface.

`DB2Connection` implements the `java.sql.Wrapper` interface.

DB2Connection methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

alternateWasUsedOnConnect

Format:

```
public boolean alternateWasUsedOnConnect()
  throws java.sql.SQLException
```

Returns `true` if the driver used alternate server information to obtain the connection. The alternate server information is available in the transient `clientRerouteServerList` information on the `DB2BaseDataSource`, which the database server updates as primary and alternate servers change.

changeDB2Password

Format:

```
public abstract void changeDB2Password(String oldPassword,
  String newPassword)
  throws java.sql.SQLException
```

Changes the password for accessing the data source, for the user of the `Connection` object.

Parameter descriptions:

oldPassword
The original password for the `Connection`.

newPassword
The new password for the `Connection`.

createArrayOf
Format:

```
Array createArrayOf(String typeName,
  Object[] elements)
  throws SQLException;
```

Creates a `java.sql.Array` object.

Parameter descriptions:

typeName
The SQL data type of the elements of the array map to. *typeName* can be a built-in data type or a distinct type.

elements
The elements that populate the `Array` object.

deregisterDB2XmlObject
Formats:

```
public void deregisterDB2XmlObject(String sqlIdSchema,
  String sqlIdName)
  throws SQLException
```

Removes a previously registered XML schema from the data source.

Parameter descriptions:

sqlIdSchema
The SQL schema name for the XML schema. *sqlIdSchema* is a String value with a maximum length of 128 bytes. The value of *sqlIdSchema* must be the string 'SYSXSR' or null. If the value of *sqlIdSchema* is null, the database system uses the string 'SYSXSR'.

sqlIdName
The SQL name for the XML schema. *sqlIdName* is a String value with a maximum length of 128 bytes. The value of *sqlIdName* must conform to the rules for an SQL identifier and cannot be null.

getDB2ClientAccountingInformation
Format:

```
public String getDB2ClientAccountingInformation()
  throws SQLException
```

Returns accounting information for the current client.

Important: `getDB2ClientAccountingInformation` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.getClientInfo` instead.

getDB2ClientApplicationInformation
Format:

```
public String getDB2ClientApplicationInformation()
  throws java.sql.SQLException
```

Returns application information for the current client.

Important: `getDB2ClientApplicationInformation` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.getClientInfo` instead.

getDB2ClientCorrelationToken

Format:

```
public String getDB2ClientCorrelationToken()
  throws SQLException
```

Returns the client correlation token for the current client.

getDB2ClientCorrelationToken applies only to connections to Db2 for z/OS.

Important: `getDB2ClientCorrelationToken` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.getClientInfo` instead.

getDB2ClientProgramId

Format:

```
public String getDB2ClientProgramId()
  throws java.sql.SQLException
```

Returns the user-defined program identifier for the client. The program identifier can be used to identify the application at the data source.

getDB2ClientProgramId does not apply to Db2 on Linux, UNIX, and Windows systems data servers.

getDB2ClientUser

Format:

```
public String getDB2ClientUser()
  throws java.sql.SQLException
```

Returns the current client user name for the connection. This name is not the user value for the JDBC connection.

Important: `getDB2ClientUser` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.getClientInfo` instead.

getDB2ClientWorkstation

Format:

```
public String getDB2ClientWorkstation()
  throws java.sql.SQLException
```

Returns current client workstation name for the current client.

Important: `getDB2ClientWorkstation` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.getClientInfo` instead.

getDB2Correlator

Format:

```
String getDB2Correlator()
  throws java.sql.SQLException
```

Returns the value of the crrtkn (correlation token) instance variable that DRDA sends with the ACCRDB command. The correlation token uniquely identifies a logical connection to a server.

getDB2CurrentPackagePath

Format:

```
public String getDB2CurrentPackagePath()
  throws java.sql.SQLException
```

Returns the list of Db2 package collections that are searched for JDBC and SQLJ packages.

The getDB2CurrentPackagePath method applies only to connections to Db2 database systems.

getDB2CurrentPackageSet

Format:

```
public String getDB2CurrentPackageSet()
  throws java.sql.SQLException
```

Returns the collection ID for the connection.

The getDB2CurrentPackageSet method applies only to connections to Db2 database systems.

getDB2ProgressiveStreaming

Format:

```
public int getDB2ProgressiveStreaming()
  throws java.sql.SQLException
```

Returns the current progressive streaming setting for the connection.

The returned value depends on whether the data source supports progressive streaming, how the progressiveStreaming property is set, and whether `DB2Connection.setProgressiveStreaming` was called:

- If the data source does not support progressive streaming, 2 (NO) is always returned, regardless of the progressiveStreaming property setting.
- If the data source supports progressive streaming, and `DB2Connection.setProgressiveStreaming` was called, the returned value is the value that `DB2Connection.setProgressiveStreaming` set.
- If the data source supports progressive streaming, and `DB2Connection.setProgressiveStreaming` was not called, the returned value is 2 (NO) if progressiveStreaming was set to `DB2BaseDataSource.NO`. If progressiveStreaming was set to `DB2BaseDataSource.YES` or was not set, the returned value is 1 (YES).

getDB2SecurityMechanism

Format:

```
public int getDB2SecurityMechanism()
  throws java.sql.SQLException
```

Returns the security mechanism that is in effect for the connection:

3
Clear text password security

4
User ID-only security

7
Encrypted password security

9
Encrypted user ID and password security

11
Kerberos security

12
Encrypted user ID and data security

13
Encrypted user ID, password, and data security

15
Plugin security

16
Encrypted user ID-only security

getDB2SystemMonitor
Format:

```
public abstract DB2SystemMonitor getDB2SystemMonitor()
  throws java.sql.SQLException
```

Returns the system monitor object for the connection. Each IBM Data Server Driver for JDBC and SQLJ connection can have a single system monitor.

getDBConcurrentAccessResolution
Format:

```
public int getDBConcurrentAccessResolution()
  throws java.sql.SQLException
```

Returns the concurrent access setting for the connection. The concurrent access setting is set by the `setDBConcurrentAccessResolution` method or by the concurrentAccessResolution property.

getDBConcurrentAccessResolution applies only to connections to Db2 for z/OS and Db2 on Linux, UNIX, and Windows systems.

getDBProgressiveStreaming
Format:

```
public int getDB2ProgressiveStreaming()
  throws java.sql.SQLException
```

Returns the current progressive streaming setting for the connection.

The returned value depends on whether the data source supports progressive streaming, how the progressiveStreaming property is set, and whether `DB2Connection.setProgressiveStreaming` was called:

- If the data source does not support progressive streaming, 2 (NO) is always returned, regardless of the progressiveStreaming property setting.
- If the data source supports progressive streaming, and `DB2Connection.setProgressiveStreaming` was called, the returned value is the value that `DB2Connection.setProgressiveStreaming` set.
- If the data source supports progressive streaming, and `DB2Connection.setProgressiveStreaming` was not called, the returned value is 2 (NO) if progressiveStreaming was set to `DB2BaseDataSource.NO`. If progressiveStreaming was set to `DB2BaseDataSource.YES` or was not set, the returned value is 1 (YES).

getDBStatementConcentrator
Format:

```
public int getDBStatementConcentrator()
  throws java.sql.SQLException
```

Returns the statement concentrator use setting for the connection. The statement concentrator use setting is set by the `setDBStatementConcentrator` method or by the statementConcentrator property.

getJccLogWriter
Format:

```
public PrintWriter getJccLogWriter()
  throws java.sql.SQLException
```

Returns the current trace destination for the IBM Data Server Driver for JDBC and SQLJ trace.

getJccSpecialRegisterProperties

Format:

```
public java.util.Properties getJccSpecialRegisterProperties()
  throws java.sql.SQLException
```

Returns a `java.util.Properties` object, in which the keys are the special registers that are supported at the target data source, and the key values are the current values of those special registers.

This method does not apply to connections to IBM Informix data sources.

getSavePointUniqueOption

Format:

```
public boolean getSavePointUniqueOption()
  throws java.sql.SQLException
```

Returns `true` if `setSavePointUniqueOption` was most recently called with a value of `true`. Returns `false` otherwise.

installDB2JavaStoredProcedure

Format:

```
public void DB2Connection.installDB2JavaStoredProcedure(
  java.io.InputStream jarFile,
  int jarFileLength,
  String jarId)
  throws java.sql.SQLException
```

Invokes the SQLJ.DB2_INSTALL_JAR stored procedure on a Db2 for z/OS server to create a new definition of a JAR file in the catalog for that server.

Parameter descriptions:

jarFile
The contents of the JAR file that is to be defined to the server.

jarFileLength
The length of the JAR file that is to be defined to the server.

jarId
The name of the JAR in the database, in the form *schema.JAR-id* or *JAR-id*. This is the name that you use when you refer to the JAR in SQL statements. If you omit *schema*, the database system uses the SQL authorization ID that is in the CURRENT SCHEMA special register. The owner of the JAR is the authorization ID in the CURRENT SQLID special register.

This method does not apply to connections to IBM Informix data sources.

isDB2Alive

Format:

```
public boolean DB2Connection.isDB2Alive()
  throws java.sql.SQLException
```

Returns `true` if the socket for a connection to the data source is still active.

Important: `isDB2Alive` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `Connection.isDBValid` instead.

isDBValid

Format:

```
public boolean DB2Connection.isDBValid(boolean throwException, int timeout)
  throws java.sql.SQLException
```

Returns `true` if the connection has not been closed and is still valid. Returns `false` otherwise.

Parameter descriptions:

throwException
Specifies whether `isDBValid` throws an `SQLException` if the connection is not valid. Possible values are:

true
`isDBValid` throws an `SQLException` if the connection is not valid.

false
`isDBValid` throws an `SQLException` only if the value of *timeout* is not valid.

timeout
The time in seconds to wait for completion of a database operation that the driver submits. The driver submits that database operation to the data source to validate the connection. If the timeout period expires before the database operation completes, `isDBValid` returns `false`. A value of 0 indicates that there is no timeout period for the database operation.

For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, `isDBValid` throws an `SQLException` if the value of *timeout* is less than 0.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, `isDBValid` throws an `SQLException` if the value of *timeout* is not equal to 0.

This method does not apply to connections to IBM Informix data sources.

reconfigureDB2Connection
Format:

```
public void reconfigureDB2Connection(java.util.Properties properties)
  throws SQLException
```

Reconfigures a connection with new settings. The connection does not need to be returned to a connection pool before it is reconfigured. This method can be called while a transaction is in progress, and can be used for trusted or untrusted connections.

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

Parameter descriptions:

properties
New properties for the connection. These properties override any properties that are already defined on the `DB2Connection` instance.

registerDB2XmlSchema
Formats:

```
public void registerDB2XmlSchema(String[] sqlIdSchema,
  String[] sqlIdName,
  String[] xmlSchemaLocations,
  InputStream[] xmlSchemaDocuments,
  int[] xmlSchemaDocumentsLengths,
  InputStream[] xmlSchemaDocumentsProperties,
  int[] xmlSchemaDocumentsPropertiesLengths,
  InputStream xmlSchemaProperties,
  int xmlSchemaPropertiesLength,
  boolean isUsedForShredding)
  throws SQLException
public void registerDB2XmlSchema(String[] sqlIdSchema,
  String[] sqlIdName,
  String[] xmlSchemaLocations,
  String[] xmlSchemaDocuments,
```

```
String[] xmlSchemaDocumentsProperties,
String xmlSchemaProperties,
boolean isUsedForShredding)
throws SQLException
```

Registers an XML schema with one or more XML schema documents. If multiple XML schema documents are processed with one call to `registerDB2XmlSchema`, those documents are processed as part of a single transaction.

The first form of `registerDB2XmlSchema` is for XML schema documents that are read from an input stream. The second form of `registerDB2XmlSchema` is for XML schema documents that are read from strings.

Parameter descriptions:

sqlIdSchema
The SQL schema name for the XML schema. Only the first element of the *sqlIdSchema* array is used. *sqlIdSchema* is a String value with a maximum length of 128 bytes. The value of *sqlIdSchema* must be the string 'SYSXSR' or null. If the value of *sqlIdSchema* is null, the database system uses the string 'SYSXSR'.

sqlIdName
The SQL name for the XML schema. Only the first element of the *sqlIdName* array is used. *sqlIdName* is a String value with a maximum length of 128 bytes. The value of *sqlIdName* must conform to the rules for an SQL identifier and cannot be null.

xmlSchemaLocations
XML schema locations for the primary XML schema documents of the schemas that are being registered. XML schema location values are normally in URI format. Each *xmlSchemaLocations* value is a String value with a maximum length of 1000 bytes. The value is used only to match the information that is specified in the XML schema document that references this document. The database system does no validation of the format, and no attempt is made to resolve the URI.

xmlSchemaDocuments
The content of the primary XML schema documents. Each *xmlSchemaDocuments* value is a String or InputStream value with a maximum length of 30 MB. The values must not be null.

xmlSchemaDocumentsLengths
The lengths of the XML schema documents in the *xmlSchemaDocuments* parameter, if the first form of `registerDB2XmlSchema` is used. Each *xmlSchemaDocumentsLengths* value is an int value.

xmlSchemaDocumentsProperties
Contains properties of the primary XML schema documents, such as properties that are used by an external XML schema versioning system. The database system does no validation of the contents of these values. They are stored in the XSR table for retrieval and used in other tools and XML schema repository implementations. Each *xmlSchemaDocumentsProperties* value is a String or InputStream value with a maximum length of 5 MB. A value is null if there are no properties to be passed.

xmlSchemaDocumentsPropertiesLengths
The lengths of the XML schema properties in the *xmlSchemaDocumentsProperties* parameter, if the first form of `registerDB2XmlSchema` is used. Each *xmlSchemaDocumentsPropertiesLengths* value is an int value.

xmlSchemaProperties
Contains properties of the entire XML schema, such as properties that are used by an external XML schema versioning system. The database system does no validation of the contents of this value. They are stored in the XSR table for retrieval and used in other tools and XML schema repository implementations. The *xmlSchemaProperties* value is a String or InputStream value with a maximum length of 5 MB. The value is null if there are no properties to be passed.

xmlSchemaPropertiesLengths
The length of the XML schema property in the *xmlSchemaProperties* parameter, if the first form of `registerDB2XmlSchema` is used. The *xmlSchemaPropertiesLengths* value is an int value.

isUsedForShredding
Indicates whether there are annotations in the schema that are to be used for XML decomposition. *isUsedForShredding* is a boolean value.

The *isUsedForShredding* parameter value must be `false` for connections to Db2 for z/OS data sources.

This method does not apply to connections to IBM Informix data sources.

setDBConcurrentAccessResolution
Format:

```
public void setDBConcurrentAccessResolution(int concurrentAccessResolution)
  throws java.sql.SQLException
```

Specifies whether the IBM Data Server Driver for JDBC and SQLJ requests that a read transaction can access a committed and consistent image of rows that are incompatibly locked by write transactions, if the data source supports accessing currently committed data, and the application isolation level is cursor stability (CS) or read stability (RS). This option has the same effect as the Db2 CONCURRENTACCESSRESOLUTION bind option. `setDBConcurrentAccessResolution` affects only statements that are created after `setDBConcurrentAccessResolution` is executed.

setDBConcurrentAccessResolution applies only to connections to Db2 for z/OS and Db2 on Linux, UNIX, and Windows systems.

Parameter descriptions:

concurrentAccessResolution
One of the following integer values:

DB2BaseDataSource.-
CONCURRENTACCESS_USE_CURRENTLY_COMMITTED (1)
The IBM Data Server Driver for JDBC and SQLJ requests that:

- Read transactions access the currently committed data when the data is being updated or deleted.
- Read transactions skip rows that are being inserted.

DB2BaseDataSource.CONCURRENTACCESS_WAIT_FOR_OUTCOME (2)
The IBM Data Server Driver for JDBC and SQLJ requests that:

- Read transactions wait for a commit or rollback operation when they encounter data that is being updated or deleted.
- Read transactions do not skip rows that are being inserted.

DB2BaseDataSource.CONCURRENTACCESS_NOT_SET (0)
Enables the data server's default behavior for read transactions when lock contention occurs. This is the default value.

setDBProgressiveStreaming
Format:

```
public void setDB2ProgressiveStreaming(int newSetting)
  throws java.sql.SQLException
```

Sets the progressive streaming setting for all `ResultSet` objects that are created on the connection.

Parameter descriptions:

newSetting
The new progressive streaming setting. Possible values are:

`DB2BaseDataSource.YES (1)`
Enable progressive streaming. If the data source does not support progressive streaming, this setting has no effect.

DB2BaseDataSource.NO (2)
Disable progressive streaming.

setDBStatementConcentrator
Format:

```
public void setDBStatementConcentrator(int statementConcentratorUse)
  throws java.sql.SQLException
```

Specifies whether the IBM Data Server Driver for JDBC and SQLJ uses the data source's statement concentrator functionality. The statement concentrator is the ability to bypass preparation of a statement when it is the same as a statement in the dynamic statement cache, except for literal values. Statement concentrator functionality applies only to SQL statements that have literals but no parameter markers. `setDBStatementConcentrator` overrides the setting of the statementConcentrator `Connection` or `DataSource` property. `setDBStatementConcentrator` affects only statements that are created after `setDBStatementConcentrator` is executed.

Parameter descriptions:

statementConcentratorUse
One of the following integer values:

DB2BaseDataSource.STATEMENT_CONCENTRATOR_OFF (1)
The IBM Data Server Driver for JDBC and SQLJ does not use the data source's statement concentrator functionality.

DB2BaseDataSource.STATEMENT_CONCENTRATOR_WITH_LITERALS (2)
The IBM Data Server Driver for JDBC and SQLJ uses the data source's statement concentrator functionality.

DB2BaseDataSource.STATEMENT_CONCENTRATOR_NOT_SET (0)
Enables the data server's default behavior for statement concentrator functionality. This is the default value.

For Db2 on Linux, UNIX, and Windows systems data sources that support statement concentrator functionality, the functionality is used if the STMT_CONC configuration parameter is set to ON at the data source. Otherwise, statement concentrator functionality is not used.

For Db2 for z/OS data sources that support statement concentrator functionality, the functionality is not used if statementConcentrator is not set.

removeDB2JavaStoredProcedure
Format:

```
public void DB2Connection.removeDB2JavaStoredProcedure(
  String jarId)
  throws java.sql.SQLException
```

Invokes the SQLJ.DB2_REMOVE_JAR stored procedure on a Db2 for z/OS server to delete the definition of a JAR file from the catalog for that server.

Parameter descriptions:

jarId
The name of the JAR in the database, in the form *schema.JAR-id* or *JAR-id*. This is the name that you use when you refer to the JAR in SQL statements. If you omit *schema*, the database system uses the SQL authorization ID that is in the CURRENT SCHEMA special register.

This method does not apply to connections to IBM Informix data sources.

replaceDB2JavaStoredProcedure
Format:

```
public void DB2Connection.replaceDB2JavaStoredProcedure(
  java.io.InputStream jarFile,
  int jarFileLength,
```

```
  String jarId)
  throws java.sql.SQLException
```

Invokes the SQLJ.DB2_REPLACE_JAR stored procedure on a Db2 for z/OS server to replace the definition of a JAR file in the catalog for that server.

Parameter descriptions:

jarFile
The contents of the JAR file that is to be replaced on the server.

jarFileLength
The length of the JAR file that is to be replace on the server.

jarId
The name of the JAR in the database, in the form *schema.JAR-id* or *JAR-id*. This is the name that you use when you refer to the JAR in SQL statements. If you omit *schema*, the database system uses the SQL authorization ID that is in the CURRENT SCHEMA special register. The owner of the JAR is the authorization ID in the CURRENT SQLID special register.

This method does not apply to connections to IBM Informix data sources.

reuseDB2Connection (trusted connection reuse)

Formats:

```
public void reuseDB2Connection(byte[] cookie,
  String user,
  String password,
  String usernameRegistry,
  byte[] userSecToken,
  String originalUser,
  java.util.Properties properties)
  throws java.sql.SQLException
public void reuseDB2Connection(byte[] cookie,
  org.ietf.GSSCredential gssCredential,
  String usernameRegistry,
  byte[] userSecToken,
  String originalUser,
  java.util.Properties properties)
  throws java.sql.SQLException
```

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

The second of these forms of reuseDB2Connection does not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

These forms of `reuseDB2Connection` are used by a trusted application server to reuse a preexisting trusted connection on behalf of a new user. Properties that can be reset are passed, including the new user ID. The database server resets the associated physical connection. If `reuseDB2Connection` executes successfully, the connection becomes available for immediate use, with different properties, by the new user.

Parameter descriptions:

cookie
A unique cookie that the JDBC driver generates for the `Connection` instance. The cookie is known only to the application server and the underlying JDBC driver that established the initial trusted connection. The application server passes the cookie that was created by the driver when the pooled connection instance was created. The JDBC driver checks that the supplied cookie matches the cookie of the underlying trusted physical connection to ensure that the request originated from the application server that established the trusted physical connection. If the

cookies match, the connection becomes available for immediate use, with different properties, by the new user .

user
The client ID that the database system uses to establish the database authorization ID. If the user was not authenticated by the application server, the application server needs to pass a client ID that represents an unauthenticated user.

password
The password for *user*.

gssCredential
If the data source uses Kerberos security, specifies a delegated credential that is passed from another principal.

userNameRegistry
A name that identifies a mapping service that maps a workstation user ID to a z/OS RACF ID. An example of a mapping service is the Integrated Security Services Enterprise Identity Mapping (EIM). The mapping service is defined by a plugin. Valid values for *userNameRegistry* are defined by the plugin providers. If *userNameRegistry* is null, no mapping of *user* is done.

userSecToken
The client's security tokens. This value is traced as part of Db2 for z/OS accounting data. The content of *userSecToken* is described by the application server and is referred to by the database system as an application server security token.

originalUser
The original user ID that was used by the application server.

properties
Properties for the reused connection.

reuseDB2Connection (untrusted reuse with reauthentication)
Formats:

```
public void reuseDB2Connection(String user,
  String password,
  java.util.Properties properties)
  throws java.sql.SQLException
public void reuseDB2Connection(
  org.ietf.jgss.GSSCredential gssCredential,
  java.util.Properties properties)
  throws java.sql.SQLException
```

The first of these forms of `reuseDB2Connection` is not supported for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

The second of these forms of `reuseDB2Connection` does not apply to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

In a heterogeneous pooling environment, these forms of `reuseDB2Connection` reuse an existing `Connection` instance after reauthentication.

Parameter description:

user
The authorization ID that is used to establish the connection.

password
The password for the authorization ID that is used to establish the connection.

gssCredential
If the data source uses Kerberos security, specifies a delegated credential that is passed from another principal.

properties
Properties for the reused connection. These properties override any properties that are already defined on the `DB2Connection` instance.

reuseDB2Connection (untrusted or trusted reuse without reauthentication)

Formats:

```
public void reuseDB2Connection(java.util.Properties properties)
  throws java.sql.SQLException
```

Reuses an existing Connection instance without reauthentication. This method is intended for reuse of a `Connection` instance when the properties do not change.

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

This method is for *dirty reuse* of a connection. This means that the connection state is not reset when the object is reused from the pool. Special register settings and property settings remain in effect unless they are overridden by passed properties. Global temporary tables are not deleted. Properties that are not specified are not re-initialized. All JDBC standard transient properties, such as the isolation level, autocommit mode, and read-only mode are reset to their JDBC defaults. Certain properties, such as `user`, `password`, `databaseName`, `serverName`, `portNumber`, `planName`, and `pkList` remain unchanged.

Parameter description:

properties
Properties for the reused connection. These properties override any properties that are already defined on the `DB2Connection` instance.

setDB2ClientAccountingInformation

Format:

```
public void setDB2ClientAccountingInformation(String info)
  throws java.sql.SQLException
```

Specifies accounting information for the connection. This information is for client accounting purposes. This value can change during a connection.

setDB2ClientAccountingToken applies only to connections to Db2 for z/OS.

`setDB2ClientAccountingInformation` sets the value in the CURRENT CLIENT_ACCTNG special register.

Parameter description:

info
User-specified accounting information.

The maximum length depends on the data server version. See “Client info properties support by the IBM Data Server Driver for JDBC and SQLJ” on page 84 for the maximum lengths.

A Java empty string ("") or a Java `null` value is valid for this parameter.

Important: `setDB2ClientAccountingInformation` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.setClientInfo` instead.

setDB2ClientApplicationInformation

Format:

```
public String setDB2ClientApplicationInformation(String info)
  throws java.sql.SQLException
```

Specifies application information for the current client.

Important: `setDB2ClientApplicationInformation` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.setClientInfo` instead.

Parameter description:

info
User-specified application information.

The maximum length depends on the data server version. See "Client info properties support by the IBM Data Server Driver for JDBC and SQLJ" on page 84 for the maximum lengths.

A Java empty string ("") or a Java `null` value is valid for this parameter.

setDB2ClientCorrelationToken
Format:

```
public String setDB2ClientCorrelationToken(String client-correlation-token)
  throws SQLException
```

Specifies a unique value that allows you to correlate your business processes across the enterprise.

`setDB2ClientCorrelationToken` sets the value in the CURRENT CLIENT_CORR_TOKEN special register. The client correlation token value is available in the accounting correlation header record of a Db2 trace, and in the -DISPLAY THREAD command output.

Important: `setDB2ClientCorrelationToken` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.setClientInfo` instead.

Parameter description:

client-correlation-token
A unique value that can be used to correlate business processes across an enterprise. The maximum length is 255 bytes.

setDB2ClientDebugInfo
Formats:

```
public void setDB2ClientDebugInfo(String debugInfo)
  throws java.sql.SQLException
public void setDB2ClientDebugInfo(String mgrInfo,
  String traceInfo)
  throws java.sql.SQLException
```

Sets a value for the CLIENT DEBUGINFO connection attribute, to notify the database system that stored procedures and user-defined functions that are using the connection are running in debug mode. CLIENT DEBUGINFO is used by the Db2 Unified Debugger. Use the first form to set the entire CLIENT DEBUGINFO string. Use the second form to modify only the session manager and trace information in the CLIENT DEBUGINFO string.

Setting the CLIENT DEBUGINFO attribute to a string of length greater than zero requires one of the following privileges:

- The DEBUGSESSION privilege
- SYSADM authority

Parameter description:

debugInfo
A string of up to 254 bytes, in the following form:

```
Mip:port,Iip,Ppid,Ttid,Cid,Llvl
```

The parts of the string are:

M*ip:port*
Session manager IP address and port number

I*ip*
Client IP address

P*pid*
Client process ID

T*tid*
Client thread ID (optional)

C*id*
Data connection generated ID

L*lvl*
Debug library diagnostic trace level

For example:

```
M9.72.133.89:8355,I9.72.133.89,P4552,T123,C1,L0
```

See the description of SET CLIENT DEBUGINFO for a detailed description of this string.

mgrInfo
A string of the following form, which specifies the IP address and port number for the Unified Debugger session manager.

```
Mip:port
```

For example:

```
M9.72.133.89:8355
```

See the description of SET CLIENT DEBUGINFO for a detailed description of this string.

trcInfo
A string of the following form, which specifies the debug library diagnostics trace level.

```
Llvl
```

For example:

```
L0
```

See the description of SET CLIENT DEBUGINFO for a detailed description of this string.

setDB2ClientProgramId
Format:

```
public abstract void setDB2ClientProgramId(String program-ID)
  throws java.sql.SQLException
```

Sets a user-defined program identifier for the connection, on Db2 for z/OS servers. That program identifier is an 80-byte string that is used to identify the caller.

setDB2ClientProgramId does not apply to Db2 on Linux, UNIX, and Windows systems or IBM Informix data servers.

The Db2 for z/OS server places the string in IFCID 316 trace records along with other statistics, so that you can identify which program is associated with a particular SQL statement.

setDB2ClientUser
Format:

```
public void setDB2ClientUser(String user)
  throws java.sql.SQLException
```

Specifies the current client user name for the connection. This name is for client accounting purposes, and is not the user value for the JDBC connection. Unlike the user for the JDBC connection, the current client user name can change during a connection.

setDB2ClientUser sets the value in the CLIENT USERID special register.

Parameter description:

user
The user ID for the current client. The maximum length depends on the server.

The maximum length depends on the data server version. See "Client info properties support by the IBM Data Server Driver for JDBC and SQLJ" on page 84 for the maximum lengths.

A Java empty string ("") or a Java `null` value is valid for this parameter.

Important: `setDB2ClientUser` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.setClientInfo` instead.

setDB2ClientWorkstation
Format:

```
public void setDB2ClientWorkstation(String name)
  throws java.sql.SQLException
```

Specifies the current client workstation name for the connection. This name is for client accounting purposes. The current client workstation name can change during a connection.

`setDB2ClientWorkstation` sets the value in the CLIENT WRKSTNNAME special register.

Parameter description:

name
The workstation name for the current client.

The maximum length depends on the data server version. See "Client info properties support by the IBM Data Server Driver for JDBC and SQLJ" on page 84 for the maximum lengths.

A Java empty string ("") or a Java `null` value is valid for this parameter.

Important: `getDB2ClientWorkstation` is deprecated in the JDBC 4.0 implementation of the IBM Data Server Driver for JDBC and SQLJ. Use `java.sql.Connection.getClientInfo` instead.

setDB2CurrentPackagePath
Format:

```
public void setDB2CurrentPackagePath(String packagePath)
  throws java.sql.SQLException
```

Specifies a list of collection IDs that the database system searches for JDBC and SQLJ packages.

The setDB2CurrentPackagePath method applies only to connections to Db2 database systems.

Parameter description:

packagePath
A comma-separated list of collection IDs.

setDB2CurrentPackageSet
Format:

```
public void setDB2CurrentPackageSet(String packageSet)
  throws java.sql.SQLException
```

Specifies the collection ID for the connection. When you set this value, you also set the collection ID of the IBM Data Server Driver for JDBC and SQLJ instance that is used for the connection.

The setDB2CurrentPackageSet method applies only to connections to Db2 database systems.

Parameter description:

packageSet
The collection ID for the connection. The maximum length for the *packageSet* value is 18 bytes. You can invoke this method as an alternative to executing the SQL SET CURRENT PACKAGESET statement in your program.

setDB2ProgressiveStreaming
Format:

```
public void setDB2ProgressiveStreaming(int newSetting)
  throws java.sql.SQLException
```

Sets the progressive streaming setting for all `ResultSet` objects that are created on the connection.

Parameter descriptions:

newSetting
The new progressive streaming setting. Possible values are:

`DB2BaseDataSource.YES` (1)
Enable progressive streaming. If the data source does not support progressive streaming, this setting has no effect.

`DB2BaseDataSource.NO` (2)
Disable progressive streaming.

setGlobalSessionVariable
Format:

```
public void setGlobalSessionVariable(String global-variable-name,
  String global-variable-value)
  throws java.sql.SQLException
```

Sets the value of a global variable. This method applies only to connections to Db2 for z/OS Version 11 or later data servers.

Parameter descriptions:

global-variable-name
The name of a global variable that is defined on the data server.

global-variable-value
The value that is assigned to the global variable.

setJccLogWriter
Formats:

```
public void setJccLogWriter(PrintWriter logWriter)
  throws java.sql.SQLException

public void setJccLogWriter(PrintWriter logWriter, int traceLevel)
  throws java.sql.SQLException
```

Enables or disables the IBM Data Server Driver for JDBC and SQLJ trace, or changes the trace destination during an active connection.

Parameter descriptions:

logWriter
An object of type `java.io.PrintWriter` to which the IBM Data Server Driver for JDBC and SQLJ writes trace output. To turn off the trace, set the value of *logWriter* to `null`.

traceLevel
Specifies the types of traces to collect. See the description of the *traceLevel* property in "Properties for the IBM Data Server Driver for JDBC and SQLJ" for valid values.

setSavePointUniqueOption
Format:

```
public void setSavePointUniqueOption(boolean flag)
  throws java.sql.SQLException
```

Specifies whether an application can reuse a savepoint name within a unit of recovery. Possible values are:

true
A `Connection.setSavepoint(savepoint-name)` method cannot specify the same value for *savepoint-name* more than once within the same unit of recovery.

false
A `Connection.setSavepoint(savepoint-name)` method can specify the same value for *savepoint-name* more than once within the same unit of recovery.

When `false` is specified, if the `Connection.setSavepoint(savepoint-name)` method is executed, and a savepoint with the name *savepoint-name* already exists within the unit of recovery, the database manager destroys the existing savepoint, and creates a new savepoint with the name *savepoint-name*.

Reuse of a savepoint is not the same as executing `Connection.releaseSavepoint(savepoint-name)`. `Connection.releaseSavepoint(savepoint-name)` releases *savepoint-name*, and any savepoints that were subsequently set.

updateDB2XmlSchema
Format:

```
public void updateDB2XmlSchema(String[] targetSqlIdSchema,
  String[] targetSqlIdName,
  String[] sourceSqlIdSchema,
  String[] sourceSqlIdName,
  String[] xmlSchemaLocations,
  boolean dropSourceSchema)
  throws SQLException
```

Updates the contents of an XML schema with the contents of another XML schema in the XML schema repository, and optionally drops the source schema. The schema documents in the target XML schema are replaced with the schema documents from the source XML schema. Before `updateDB2XmlSchema` can be called, registration of the source and target XML schemas must be completed.

The SQL ALTERIN privilege is required for updating the target XML schema. The SQL DROPIN privilege is required for dropping the source XML schema.

Parameter descriptions:

targetSqlIdSchema
The SQL schema name for a registered XML schema that is to be updated. *targetSqlIdSchema* is a String value with a maximum length of 128 bytes.

targetSqlIdName
The name of the registered XML schema that is to be updated. *targetSqlIdName* is a String value with a maximum length of 128 bytes.

sourceSqlIdSchema
The SQL schema name for a registered XML schema that is used to update the target XML schema. *sourceSqlIdSchema* is a String value with a maximum length of 128 bytes.

sourceSqlIdName
The name of the registered XML schema that is used to update the target XML schema. *sourceSqlIdName* is a String value with a maximum length of 128 bytes.

dropSourceSchema
Indicates whether the source XML schema is to be dropped after the target XML schema is updated. *dropSourceSchema* is a boolean value. `false` is the default.

This method does not apply to connections to IBM Informix data sources.

zLoad

Formats:

```
public LoadResult zLoad(String loadstmt,
  String dataFilename)
  throws SQLException

public LoadResult zLoad(String loadstmt,
  String dataFilename,
  String utilid)
  throws SQLException

public LoadResult zLoad(String loadstmtOrFile,
  boolean isLoadStmtInFile,
  String dataFilename)
  throws SQLException

public LoadResult zLoad(String loadstmtOrFile,
  boolean isLoadstmtInFile,
  String dataFilename,
  String utilid)
  throws SQLException
```

Loads data into a Db2 for z/OS table and returns a `LoadResult` object, which contains the LOAD messages and the return code that are returned from the data server.

Parameter descriptions:

loadstmt
Specifies the LOAD statement. *loadstmt* is a `String` value with a maximum length of 32704 bytes.

dataFilename
Specifies the file name of an external file, the contents of which you want to load into a Db2 for z/OS table. *dataFilename* is a `String` value.

utilid
Specifies the utility ID for the LOAD statement. *utilid* is a `String` value with a maximum length of 16 bytes.

loadstmtOrFile
Specifies the LOAD statement, or the path for the file that contains the LOAD statement.

isLoadStmtInFile
Specifies whether the LOAD statement is in a file.

This method applies only to connections to Db2 for z/OS Version 12 or later data servers.

Related concepts

“Problem diagnosis with the IBM Data Server Driver for JDBC and SQLJ” on page 629
The IBM Data Server Driver for JDBC and SQLJ includes diagnostic tools and traces for diagnosing problems during connection and SQL statement execution.

Related tasks

“Providing extended client information to the data source with IBM Data Server Driver for JDBC and SQLJ-only methods” on page 82
A set of IBM Data Server Driver for JDBC and SQLJ-only methods provide extra information about the client to the server. This information can be used for accounting, workload management, or debugging.

“Loading a Db2 for z/OS table by using an IBM Data Server Driver for JDBC and SQLJ method” on page 105
The `DB2Connection.zLoad` method lets you load a Db2 for z/OS table from a Java application.

Related reference

“Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 servers” on page 253
Some of the IBM Data Server Driver for JDBC and SQLJ properties apply to Db2 data servers only.

“IBM Data Server Driver for JDBC and SQLJ properties for Db2 on Linux, UNIX, and Windows systems” on page 270

Some of the IBM Data Server Driver for JDBC and SQLJ properties apply only to Db2 on Linux, UNIX, and Windows systems servers.

"LoadResult class" on page 490
The `com.ibm.db2.jcc.LoadResult` class provides methods for returning the results of a `DB2Connection.zLoad` invocation.

DB2ConnectionPool class

The `com.ibm.db2.jcc.dbpool.DB2ConnectionPool` class provides connection pooling support.

In addition to providing connection pooling support, a `DB2ConnectionPool` instance supports all methods and properties of the `DB2ConnectionPoolDataSource` class.

The `DB2ConnectionPool` class is supported in IBM Data Server Driver for JDBC and SQLJ version 4.29.24 or later.

DB2ConnectionPool constructors

Formats:

```
public DB2ConnectionPool()
  throws java.sql.SQLException
public DB2ConnectionPool(String url, Properties properties)
  throws java.sql.SQLException
DB2ConnectionPool(Db2SimpleDataSource ds)
  throws java.sql.SQLException
DB2ConnectionPool(DB2ConnectionPoolDataSource cpds)
  throws java.sql.SQLException
```

Example: Default constructor

```
DB2ConnectionPool pool = new DB2ConnectionPool();
```

Example: Constructor with a JDBC URL as an argument

```
String URL = "jdbc:db2://server:port/databasename:traceLevel=-1";
Properties props = new Properties();
props.put("user", "user");
props.put("password", "pwd");
D2ConnectionPool pool = new DB2ConnectionPool(URL, props);
```

Example: Constructor with a DB2SimpleDataSource instance as an argument

```
DB2SimpleDataSource ds = new DB2SimpleDataSource();
ds.setServerName("serverName");
ds.setPortNumber(3950);
ds.setDataBaseName("databasename");
ds.setDriverType(2);
DB2ConnectionPool pool = new DB2ConnectionPool(ds);
```

Example: Constructor with a DB2ConnectionPoolDataSource instance as an argument

```
DB2ConnectionPoolDataSource cpds=new DB2ConnectionPoolDataSource();
cpds.setServerName("serverName");
cpds.setPortNumber(3950);
cpds.setDataBaseName("databasename");
cpds.setDriverType(2);
DB2ConnectionPool pool = new DB2ConnectionPool(cpds);
```

DB2ConnectionPool properties

These properties have a `setXXX` method to set the value of the property and a `getXXX` method to retrieve the value.

A `setXXX` method has this form:

```
void setProperty-name(data-type property-value)
```

A getXXX method has this form:

```
data-type getProperty-name()
```

Property-name is the unqualified property name, with the first character capitalized.

The following table lists the IBM Data Server Driver for JDBC and SQLJ properties and their data types.

Table 98. DB2ConnectionPool properties and their data types

Property name	Data type
acquireIncrement	int
acquireRetryAttempts	int
acquireRetryDelay	int
autoCommit	boolean
connectionTimeout	int
databaseName	String
driverType	int
initialPoolSize	int
loginTimeout	int
logWriter	java.io.PrintWriter
maxIdleTime	int
maxPoolSize	int
password	String
poolLoggingFrequency	int
portNumber	int
preferredTestQuery	int
serverName	int
testConnectionOnCheckin	int
testConnectionOnCheckout	int
traceFile	String
traceLevel	int
user	int

For detailed descriptions of the properties, see "Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 servers" on page 253.

DB2ConnectionPool methods

getConnection

Format:

```
public java.sql.Connection getConnection()
  throws java.sql.SQLException
```

Establishes the initial connection in a connection pooling environment.

getDataSource

Formats:

```
public DB2ConnectionPoolDataSource getDataSource()
```

Returns a DB2ConnectionPoolDataSource object on which additional properties can be set.

getPoolStats

Format:

```
public String getPoolStats()
```

Returns connection pooling statistics.

testConnection

Format:

```
public void testConnection()
  throws java.sql.SQLException
```

Tests the pooled connection.

How properties can be set when you construct DB2ConnectionPool objects

The way that you set properties on a DB2ConnectionPool object depends on the constructor signature constructor.

For each DB2ConnectionPool object, there is an underlying DB2ConnectionPoolDataSource object. If you use a DB2ConnectionPool constructor format that does not support a property directly, you can set the property on the underlying DB2ConnectionPoolDataSource object.

The following table lists the constructor signatures and how properties can be set when you use each type of constructor.

Constructor signature	How properties can be set
`public DB2ConnectionPool()`	These properties can be set on the DB2ConnectionPool object: • user • password • serverName • portNumber • databaseName • traceFile • traceLevel • loginTimeout • connectionTimeout Any other properties can be set on the underlying DB2ConnectionPoolDataSource object.

Constructor signature	How properties can be set
public DB2ConnectionPool(String *url*, Properties *properties*)	These properties can be set on the url or on the Properties object: • user • password • serverName • portNumber • databaseName Any other properties can be set on the underlying `DB2ConnectionPoolDataSource` object.
DB2ConnectionPool(DB2SimpleDataSource *ds*)	These properties can be set on the `DB2SimpleDataSource` object: • user • password • serverName • portNumber • databaseName • traceFile • traceLevel • loginTimeout • connectionTimeout Any other properties can be set on the underlying `DB2ConnectionPoolDataSource` object.
DB2ConnectionPool(DB2ConnectionPoolDataSource *cpds*)	All properties can be set on the `DB2ConnectionPoolDataSource` object.

Example

Suppose that you are constructing a `DB2ConnectionPool` object using the constructor with the `DB2SimpleDataSource` parameter. You need to set the following properties on the `DB2ConnectionPool` object:

- serverName
- portNumber
- databaseName
- driverType
- maxRowsetSize

You can set serverName, portNumber, and databaseName on the `DB2SimpleDataSource` object that is the parameter of the `DB2ConnectionPool` constructor. You cannot set driverType and maxRowsetSize on the `DB2SimpleDataSource` object, so you need to set them on the `DB2ConnectionPoolDataSource` object that underlies the `DB2ConnectionPool` object. Use code like this to set the properties.

```
DB2SimpleDataSource ds = new DB2SimpleDataSource();
                                          // Construct a DB2SimpleDataSource object
ds.setServerName("myserver");             // Set the serverName, portNumber, and
ds.setPortNumber(3950);                   // database properties on the
ds.setDataBaseName("mydb");               // DB2SimpleDataSource object

DB2ConnectionPool pool = new DB2ConnectionPool(ds);
```

```
                                        // Construct a DB2ConnectionPool object
                                        // using the DB2SimpleDataSource object
DB2ConnectionPoolDataSource pooledDataSource =
 pool.getDataSource();                  // Retrieve the DB2ConnectionPoolDataSource
                                        // object that underlies the
                                        // DB2ConnectionPool object
pooledDataSource.setDriverType(2);      // Set driverType and maxRowsetSize on
pooledDataSource.setMaxRowsetSize(450); // the DB2ConnectionPoolDataSource object
```

Related concepts

"JDBC and SQLJ connection pooling support" on page 619
Connection pooling is supported by the IBM Data Server Driver for JDBC and SQLJ.

Related reference

"Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 servers" on page 253
Some of the IBM Data Server Driver for JDBC and SQLJ properties apply to Db2 data servers only.

DB2ConnectionPoolDataSource class

`DB2ConnectionPoolDataSource` is a factory for `PooledConnection` objects. An object that implements this interface is registered with a naming service that is based on the Java Naming and Directory Interface (JNDI).

The `com.ibm.db2.jcc.DB2ConnectionPoolDataSource` class extends the `com.ibm.db2.jcc.DB2BaseDataSource` class, and implements the `javax.sql.ConnectionPoolDataSource`, `java.io.Serializable`, and `javax.naming.Referenceable` interfaces.

DB2ConnectionPoolDataSource properties

These properties are defined only for the IBM Data Server Driver for JDBC and SQLJ. "Properties for the IBM Data Server Driver for JDBC and SQLJ" for explanations of these properties.

These properties have a `setXXX` method to set the value of the property and a `getXXX` method to retrieve the value. A `setXXX` method has this form:

```
void setProperty-name(data-type property-value)
```

A `getXXX` method has this form:

```
data-type getProperty-name()
```

Property-name is the unqualified property name, with the first character capitalized.

The following table lists the IBM Data Server Driver for JDBC and SQLJ properties and their data types.

Table 99. DB2ConnectionPoolDataSource properties and their data types

Property name	Data type
com.ibm.db2.jcc.DB2ConnectionPoolDataSource.maxStatements	int

DB2ConnectionPoolDataSource methods

getDB2PooledConnection

Formats:

```
public DB2PooledConnection getDB2PooledConnection(String user,
  String password,
  java.util.Properties properties)
  throws java.sql.SQLException
public DB2PooledConnection getDB2PooledConnection(
  org.ietf.jgss.GSSCredential gssCredential,
  java.util.Properties properties)
  throws java.sql.SQLException
```

Establishes the initial untrusted connection in a heterogeneous pooling environment.

The first form `getDB2PooledConnection` provides a user ID and password. The second form of `getDB2PooledConnection` is for connections that use Kerberos security.

Parameter descriptions:

user
The authorization ID that is used to establish the connection.

password
The password for the authorization ID that is used to establish the connection.

gssCredential
If the data source uses Kerberos security, specifies a delegated credential that is passed from another principal.

properties
Properties for the connection.

getDB2TrustedPooledConnection
Formats:

```
public Object[] getDB2TrustedPooledConnection(String user,
  String password,
  java.util.Properties properties)
  throws java.sql.SQLException
public Object[] getDB2TrustedPooledConnection(
  java.util.Properties properties)
  throws java.sql.SQLException
public Object[] getDB2TrustedPooledConnection(
  org.ietf.jgss.GSSCredential gssCredential,
  java.util.Properties properties)
  throws java.sql.SQLException
```

An application server using a system authorization ID uses this method to establish a trusted connection.

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

The following elements are returned in Object[]:

- The first element is a trusted `DB2PooledConnection` instance.
- The second element is a unique cookie for the generated pooled connection instance.

The first form `getDB2TrustedPooledConnection` provides a user ID and password, while the second form of `getDB2TrustedPooledConnection` uses the user ID and password of the `DB2ConnectionPoolDataSource` object. The third form of `getDB2TrustedPooledConnection` is for connections that use Kerberos security.

Parameter descriptions:

user
The data server authorization ID that is used to establish the trusted connection to the database server.

password
The password for the authorization ID that is used to establish the trusted connection.

gssCredential
If the data source uses Kerberos security, specifies a delegated credential that is passed from another principal.

properties
Properties for the connection.

Related concepts

"JDBC and SQLJ connection pooling support" on page 619
Connection pooling is supported by the IBM Data Server Driver for JDBC and SQLJ.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

DB2DatabaseMetaData interface

The `com.ibm.db2.jcc.DB2DatabaseMetaData` interface extends the `java.sql.DatabaseMetaData` interface.

DB2DatabaseMetaData methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getDatabaseFunctionalLevel
Format:

```
public String getDatabaseFunctionalLevel()
throws java.sql.SQLException
```

For a new `Connection` instance, returns the function level or build level of the data server. For a Db2 on Linux, UNIX, and Windows systems data server, this value is the build level: for example, S1612011300. For a Db2 12 for z/OS data server with the PTF for APAR PI74456 applied, or later, this value is the function level: for example, V12R1M500. For a data server that does not support function levels, null is returned.

isIDSDatabaseAnsiCompliant
Format:

```
public boolean isIDSDatabaseAnsiCompliant();
```

Returns `true` if the current active IBM Informix database is ANSI-compliant. Returns false otherwise.

An ANSI-compliant database is a database that was created with the WITH LOG MODE ANSI option.

This method applies to connections to IBM Informix data sources only. An `SQLException` is thrown if the data source is not an IBM Informix data source.

isIDSDatabaseLogging
Format:

```
public boolean isIDSDatabaseLogging();
```

Returns `true` if the current active IBM Informix database supports logging. Returns false otherwise.

An IBM Informix database that supports logging is a database that was created with the WITH LOG MODE ANSI option, the WITH BUFFERED LOG, or the WITH LOG option.

This method applies to connections to IBM Informix data sources only. An `SQLException` is thrown if the data source is not an IBM Informix data source.

isResetRequiredForDB2eWLM
Format:

```
public boolean isResetRequiredForDB2eWLM();
```

Returns `true` if the target database server requires clean reuse to support eWLM. Returns false otherwise.

supportsDB2ProgressiveStreaming
Format:

```
public boolean supportsDB2ProgressiveStreaming();
```

Returns `true` if the target data source supports progressive streaming. Returns false otherwise.

getDriverDB2ConnectLevel
Identifies the version of Db2 Connect and the IBM® Data Server Driver for JDBC and SQLJ version that an application is using for a connection to a data server.

DB2Diagnosable interface

The `com.ibm.db2.jcc.DB2Diagnosable` interface provides a mechanism for getting additional diagnostic information from an `SQLException`.

DB2Diagnosable methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getSqlca
Format:

```
public DB2Sqlca getSqlca();
```

Returns a `DB2Sqlca` object from a `java.sql.Exception` that is produced under a IBM Data Server Driver for JDBC and SQLJ.

getThrowable
Format:

```
public Throwable getThrowable();
```

Returns a `java.lang.Throwable` object from a `java.sql.Exception` that is produced under a IBM Data Server Driver for JDBC and SQLJ.

printTrace
Format:

```
static public void printTrace(java.io.PrintWriter printWriter,
  String header);
```

Prints diagnostic information after a `java.sql.Exception` is thrown under a IBM Data Server Driver for JDBC and SQLJ.

Parameter descriptions:

printWriter
The destination for the diagnostic information.

header
User-defined information that is printed at the beginning of the output.

Related tasks

“Handling SQL warnings in an SQLJ application” on page 173
Other than a +100 SQL error code on a SELECT INTO statement, warnings from the data server do not throw SQLExceptions. To handle warnings from the data server, you need to give the program access to the `java.sql.SQLWarning` class.

“Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ” on page 111

As in all Java programs, error handling for JDBC applications is done using `try/catch` blocks. Methods throw exceptions when an error occurs, and the code in the `catch` block handles those exceptions.

DB2DataSource class

The `com.ibm.db2.jcc.DB2DataSource` class extends the `DB2BaseDataSource` class, and implements the `javax.sql.DataSource`, `java.io.Serializable`, and `javax.naming.Referenceable` interfaces.

DB2DataSource methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

setSpecialRegisters

Format:

```
public void setSpecialRegisters(java.util.Properties properties)
  throws java.sql.SQLException
```

For each key and value pair in the `java.util.Properties` object, sets the data server special register that is specified by the key to the corresponding value.

This method does not apply to connections to IBM Informix data servers.

Parameter description:

properties

A `java.util.Properties` object that contains key and value pairs, in which each key is the name of a special register, and each value is the value to which you want to set that special register. For example, suppose that `ds` is a previously defined `DataSource` object. Set the property values in the following way.

```
Properties prop = new Properties();
prop.put ("CURRENT SCHEMA", "SYSPROC");
prop.put ("CURRENT PACKAGESET", "PRODUCTION");
((com.ibm.db2.jcc.DB2BaseDataSource) ds).setSpecialRegisters(prop);
```

Certain special registers can be set through IBM Data Server Driver for JDBC and SQLJ properties. If you set a special register value by setting one of those properties in a `java.util.Properties` object, and then use `setSpecialRegisters` to set a value for the same special register, the value that is set through `setSpecialRegisters` overrides the value that is set through the property. In the following example, CURRENT SCHEMA is set to USER002:

```
Properties prop = new Properties();
((com.ibm.db2.jcc.DB2BaseDataSource) ds).setCurrentSchema("USER001");
properties. put ("CURRENT SCHEMA", "USER002");
((com.ibm.db2.jcc.DB2BaseDataSource) ds).setSpecialRegisters(prop);
```

For a complete description of the rules for using setSpecialRegisters to set special registers on Db2 for z/OS data servers, see General rules for special registers (Db2 SQL).

setGlobalSessionVariables

Format:

```
public void setGlobalSessionVariables(java.util.Properties properties)
  throws java.sql.SQLException
```

For each key and value pair in the `java.util.Properties` object, sets the session variable that is specified by the key to the corresponding value.

This method applies only to connections to Db2 for z/OS Version 11 or later data servers.

Parameter description:

properties
A `java.util.Properties` object that contains key and value pairs, in which each key is the name of a session variable, and each value is the value to which you want to set that session variable. For example, suppose that `ds` is a previously defined `DataSource` object. Set the property values in the following way.

```
Properties prop = new Properties();
prop.put ("SESSION.TEST", "TEST FAILED");
prop.put ("SYSIBMADM.GET_ARCHIVE", "Y");
((com.ibm.db2.jcc.DB2BaseDataSource) ds).setGlobalSessionVariables(prop);
```

DB2Driver class

The `com.ibm.db2.jcc.DB2Driver` class extends the `java.sql.Driver` interface.

DB2Driver methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

changeDB2Password
Format:

```
public static void changeDB2Password (String url,
 String userid,
 String oldPassword,
 String newPassword)
 throws java.sql.SQLException
```

Changes the password for accessing a data server that is specified by the `url` parameter, for the user that is specified by the `userid` parameter. This method can change an unexpired or expired password.

`changeDB2Password` is supported for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

`changeDB2Password` is not supported for connections to IBM Informix.

Parameter descriptions:

url
The URL for the data server for which a user's password is being changed. The *url* value uses the syntax for a URL for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

userid
The user whose password is being changed.

oldPassword
The original password for the user.

newPassword
The new password for the user.

Related reference
“URL format for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity” on page 14

If you are using type 4 connectivity in your JDBC application, and you are making a connection using the `DriverManager` interface, you need to specify a URL in the `DriverManager.getConnection` call that indicates type 4 connectivity.

DB2ExceptionFormatter class

The `com.ibm.db2.jcc.DB2ExceptionFormatter` class contains methods for printing diagnostic information to a stream.

DB2ExceptionFormatter methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

printTrace

Formats:

```
static public void printTrace(java.sql.SQLException sqlException,
  java.io.PrintWriter printWriter, String header)

static public void printTrace(DB2Sqlca sqlca,
  java.io.PrintWriter printWriter, String header)

static public void printTrace(java.lang.Throwable throwable,
  java.io.PrintWriter printWriter, String header)
```

Prints diagnostic information after an exception is thrown.

Parameter descriptions:

sqlException|sqlca|throwable
The exception that was thrown during a previous JDBC or Java operation.

printWriter
The destination for the diagnostic information.

header
User-defined information that is printed at the beginning of the output.

Related concepts

"Example of a trace program under the IBM Data Server Driver for JDBC and SQLJ" on page 637
You might want to write a single class that includes methods for tracing under the `DriverManager` interface, as well as the `DataSource` interface.

DB2FileReference class

The `com.ibm.db2.jcc.DB2FileReference` class is an abstract class that defines methods that support insertion of data into tables from file reference variables. This class applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS Version 9 or later.

DB2FileReference fields

The following constants define types codes only for the IBM Data Server Driver for JDBC and SQLJ.

public static final short MAX_FILE_NAME_LENGTH = 255
The maximum length of the file name for a file reference variable.

DB2FileReference methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getDriverType

Format:

```
public int getDriverType()
```

Returns the server data type of the file reference variable. This type is one of the values in `com.ibm.db2.jcc.DB2Types`.

getFileEncoding
Format:

```
public String getFileEncoding()
```

Returns the encoding of the data in the file for a `DB2FileReference` object.

getFileName
Format:

```
public String getFileName()
```

Returns the file name for a `DB2FileReference` object.

getFileCcsid
Format:

```
public int getFileCcsid()
```

Returns the CCSID of the data in the file for a `DB2FileReference` object.

setFileName
Format:

```
public String setFileName(String fileName)
  throws java.sql.SQLException
```

Sets the file name in a `DB2FileReference` object.

Parameter descriptions:

fileName
The name of the input file for the file reference variable. The name must specify an existing HFS file.

DB2JCCPlugin class

The `com.ibm.db2.jcc.DB2JCCPlugin` class is an abstract class that defines methods that can be implemented to provide Db2 on Linux, UNIX, and Windows systems plug-in support. This class applies only to Db2 on Linux, UNIX, and Windows systems.

DB2JCCPlugin methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getTicket
Format:

```
public abstract byte[] getTicket(String user,
  String password,
  byte[] returnedToken)
  throws org.ietf.jgss.GSSException
```

Retrieves a Kerberos ticket for a user.

Parameter descriptions:

user
The user ID for which the Kerberos ticket is to be retrieved.

password
The password for *user*.

returnedToken

DB2JSONResultSet interface

The `com.ibm.db2.jcc.DB2JSONResultSet` interface is used to convert the contents of JDBC `ResultSet` objects to JSON documents and snippets.

The `DB2JSONResultSet` interface is available only in IBM Data Server Driver for JDBC and SQLJ version 4.18 or later.

DB2JSONResultSet methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

close

Format:

```
public void close()
  throws java.sql.SQLException
```

Closes a `DB2JSONResultSet` object.

getAsciiStream

Format:

```
public InputStream getAsciiStream()
  throws java.sql.SQLException
```

Returns a `java.io.InputStream` object that contains the contents of a `DB2JSONResultSet` object. If the contents of the object contain any non-ASCII characters, an encoding error is returned in the `SQLException`.

getCharacterStream

Format:

```
public Reader getCharacterStream()
  throws java.sql.SQLException
```

Returns a `java.io.Reader` object on which applications can call methods to read JSON documents incrementally.

getCurrentRow

Format:

```
public String getCurrentRow()
  throws java.sql.SQLException
```

Returns the current row of a `DB2JSONResultSet` object as a JSON snippet.

next

Format:

```
public String next()
  throws java.sql.SQLException
```

Moves the cursor position to the next row of a `DB2JSONResultSet` object. Returns `false` if there are no more rows to return.

toJSONString

Format:

```
public String toJSONString()
  throws java.sql.SQLException
```

Returns the contents of a `DB2JSONResultSet` object, starting with the current row, as a `String`. After this method is executed, the cursor points to the last row of the `DB2JSONResultSet` object. A subsequent `next` call returns `false`.

DB2ParameterMetaData interface

The `com.ibm.db2.jcc.DB2ParameterMetaData` interface extends the `java.sql.ParameterMetaData` interface.

DB2ParameterMetaData methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getMaxStringUnitBits

Format:

```
public int getMaxStringUnitBits (int param)
  throws java.sql.SQLException
```

Returns the maximum number of bits in a string unit for single-byte and double-byte character data types. The value that is returned is:

8
For a character column that is defined with OCTETS.

16
For a character column that is defined with CODEUNITS16.

32
For a character column that is defined with CODEUNITS32.

Parameter descriptions:

param
The ordinal position of a parameter in the CALL statement.

This method applies only to connections to Db2 on Linux, UNIX, and Windows systems Version 10.5 or later data servers.

getParameterMarkerNames

Format:

```
public String[] getParameterMarkerNames()
  throws java.sql.SQLException
```

Returns a list of the parameter marker names that are used in an SQL statement.

This method returns null if the enableNamedParameterMarkers property is set `DB2BaseDataSource.NOT_SET` or `DB2BaseDataSource.NO`, or if there are no named parameter markers in the SQL statement.

getProcedureParameterName

Format:

```
public String getProcedureParameterName(int param)
  throws java.sql.SQLException
```

Returns the name in the CREATE PROCEDURE statement of a parameter in an SQL CALL statement. If the parameter has no name in the CREATE PROCEDURE statement, the ordinal position of the parameter in the CREATE PROCEDURE statement is returned.

Parameter descriptions:

param
The ordinal position of the parameter in the CALL statement.

This method applies to connections to Db2 on Linux, UNIX, and Windows systems 9.7 or later data servers only.

DB2PooledConnection class

The `com.ibm.db2.jcc.DB2PooledConnection` class provides methods that an application server can use to switch users on a preexisting trusted connection.

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

DB2PooledConnection methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getConnection (untrusted or trusted reuse without reauthentication)

Format:

```
public DB2Connection getConnection()
  throws java.sql.SQLException
```

This method is for *dirty reuse* of a connection. This means that the connection state is not reset when the object is reused from the pool. Special register settings and property settings remain in effect unless they are overridden by passed properties. Global temporary tables are not deleted. Properties that are not specified are not re-initialized. All JDBC standard transient properties, such as the isolation level, autocommit mode, and read-only mode are reset to their JDBC defaults. Certain properties, such as `user`, `password`, `databaseName`, `serverName`, `portNumber`, `planName`, and `pkList` remain unchanged.

getDB2Connection (trusted reuse)

Formats:

```
public DB2Connection getDB2Connection(byte[] cookie,
  String user,
  String password,
  String userRegistry,
  byte[] userSecToken,
  String originalUser,
  java.util.Properties properties)
  throws java.sql.SQLException
public Connection getDB2Connection(byte[] cookie,
  org.ietf.GSSCredential gssCredential,
  String usernameRegistry,
  byte[] userSecToken,
  String originalUser,
  java.util.Properties properties)
  throws java.sql.SQLException
```

Switches the user that is associated with a trusted connection without authentication.

The second form of getDB2Connection is supported only for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

Parameter descriptions:

cookie

A unique cookie that the JDBC driver generates for the `Connection` instance. The cookie is known only to the application server and the underlying JDBC driver that established the initial trusted connection. The application server passes the cookie that was created by the driver when the pooled connection instance was created. The JDBC driver checks that the supplied cookie matches the cookie of the underlying trusted physical connection to ensure that the request originated from the application server that established the trusted physical connection. If the

cookies match, the connection can become available, with different properties, for immediate use by a new user .

user
The client identity that is used by the data source to establish the authorization ID for the database server. If the user was not authenticated by the application server, the application server must pass a user identity that represents an unauthenticated user.

password
The password for *user*.

gssCredential
If the data source uses Kerberos security, specifies a delegated credential that is passed from another principal.

userNameRegistry
A name that identifies a mapping service that maps a workstation user ID to a z/OS RACF ID. An example of a mapping service is the Integrated Security Services Enterprise Identity Mapping (EIM). The mapping service is defined by a plugin. Valid values for *userNameRegistry* are defined by the plugin providers. If *userNameRegistry* is null, the connection does not use a mapping service.

userSecToken
The client's security tokens. This value is traced as part of Db2 for z/OS accounting data. The content of *userSecToken* is described by the application server and is referred to by the data source as an application server security token.

originalUser
The client identity that sends the original request to the application server. *originalUser* is included in Db2 for z/OS accounting data as the original user ID that was used by the application server.

properties
Properties for the reused connection. These properties override any properties that are already defined on the `DB2PooledConnection` instance.

getDB2Connection (untrusted reuse with reauthentication)
Formats:

```
public DB2Connection getDB2Connection(
  String user,
  String password,
  java.util.Properties properties)
  throws java.sql.SQLException
public DB2Connection getDB2Connection(org.ietf.jgss.GSSCredential gssCredential,
  java.util.Properties properties)
  throws java.sql.SQLException
```

Switches the user that is associated with a untrusted connection, with authentication.

The first form `getDB2Connection` provides a user ID and password. The second form of `getDB2Connection` is for connections that use Kerberos security.

Parameter descriptions:

user
The user ID that is used by the data source to establish the authorization ID for the database server.

password
The password for *user*.

properties
Properties for the reused connection. These properties override any properties that are already defined on the `DB2PooledConnection` instance.

getDB2Connection (untrusted or trusted reuse without reauthentication)
Formats:

```
public java.sql.Connection getDB2Connection(
  java.util.Properties properties)
  throws java.sql.SQLException
```

Reuses an untrusted connection, without reauthentication.

This method is for *dirty reuse* of a connection. This means that the connection state is not reset when the object is reused from the pool. Special register settings and property settings remain in effect unless they are overridden by passed properties. Global temporary tables are not deleted. Properties that are not specified are not re-initialized. All JDBC standard transient properties, such as the isolation level, autocommit mode, and read-only mode are reset to their JDBC defaults. Certain properties, such as `user`, `password`, `databaseName`, `serverName`, `portNumber`, `planName`, and `pkList` remain unchanged.

Parameter descriptions:

properties
Properties for the reused connection. These properties override any properties that are already defined on the `DB2PooledConnection` instance.

Related concepts

"JDBC and SQLJ connection pooling support" on page 619
Connection pooling is supported by the IBM Data Server Driver for JDBC and SQLJ.

Related reference

"DB2ConnectionPoolDataSource class" on page 433
`DB2ConnectionPoolDataSource` is a factory for `PooledConnection` objects. An object that implements this interface is registered with a naming service that is based on the Java Naming and Directory Interface (JNDI).

DB2PoolMonitor class

The `com.ibm.db2.jcc.DB2PoolMonitor` class provides methods for monitoring the global transport objects pool that is used for the connection concentrator and sysplex workload balancing.

DB2PoolMonitor fields

The following fields are defined only for the IBM Data Server Driver for JDBC and SQLJ.

public static final int TRANSPORT_OBJECT = 1
This value is a parameter for the `DB2PoolMonitor.getPoolMonitor` method.

DB2PoolMonitor methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

agedOutObjectCount
Format:

```
public abstract int agedOutObjectCount()
```

Retrieves the number of objects that exceeded the idle time that was specified by db2.jcc.maxTransportObjectIdleTime and were deleted from the pool.

createdObjectCount
Format:

```
public abstract int createdObjectCount()
```

Retrieves the number of objects that the IBM Data Server Driver for JDBC and SQLJ created since the pool was created.

getMonitorVersion
Format:

```
public int getMonitorVersion()
```

Retrieves the version of the DB2PoolMonitor class that is shipped with the IBM Data Server Driver for JDBC and SQLJ.

getPoolMonitor
Format:

```
public static DB2PoolMonitor getPoolMonitor(int monitorType)
```

Retrieves an instance of the `DB2PoolMonitor` class.

Parameter descriptions:

monitorType
The monitor type. This value must be DB2PoolMonitor.TRANSPORT_OBJECT.

heavyWeightReusedObjectCount
Format:

```
public abstract int heavyWeightReusedObjectCount()
```

Retrieves the number of objects that were reused from the pool.

lightWeightReusedObjectCount
Format:

```
public abstract int lightWeightReusedObjectCount()
```

Retrieves the number of objects that were reused but were not in the pool. This can happen if a Connection object releases a transport object at a transaction boundary. If the Connection object needs a transport object later, and the original transport object has not been used by any other Connection object, the Connection object can use that transport object.

longestBlockedRequestTime
Format:

```
public abstract long longestBlockedRequestTime()
```

Retrieves the longest amount of time that a request was blocked, in milliseconds.

numberOfConnectionReleaseRefused
Format:

```
public abstract int numberOfConnectionReleaseRefused()
```

Retrieves the number of times that the release of a connection was refused.

numberOfRequestsBlocked
Format:

```
public abstract int numberOfRequestsBlocked()
```

Retrieves the number of requests that the IBM Data Server Driver for JDBC and SQLJ made to the pool that the pool blocked because the pool reached its maximum capacity. A blocked request might be successful if an object is returned to the pool before the db2.jcc.maxTransportObjectWaitTime is exceeded and an exception is thrown.

numberOfRequestsBlockedDataSourceMax
Format:

```
public abstract int numberOfRequestsBlockedDataSourceMax()
```

Retrieves the number of requests that the IBM Data Server Driver for JDBC and SQLJ made to the pool that the pool blocked because the pool reached the maximum for the `DataSource` object.

numberOfRequestsBlockedPoolMax
Format:

```
public abstract int numberOfRequestsBlockedPoolMax()
```

Retrieves the number of requests that the IBM Data Server Driver for JDBC and SQLJ made to the pool that the pool blocked because the maximum number for the pool was reached.

removedObjectCount
Format:

```
public abstract int removedObjectCount()
```

Retrieves the number of objects that have been deleted from the pool since the pool was created.

shortestBlockedRequestTime
Format:

```
public abstract long shortestBlockedRequestTime()
```

Retrieves the shortest amount of time that a request was blocked, in milliseconds.

successfullRequestsFromPool
Format:

```
public abstract int successfullRequestsFromPool()
```

Retrieves the number of successful requests that the IBM Data Server Driver for JDBC and SQLJ has made to the pool since the pool was created. A successful request means that the pool returned an object.

totalPoolObjects
Format:

```
public abstract int totalPoolObjects()
```

Retrieves the number of objects that are currently in the pool.

totalRequestsToPool
Format:

```
public abstract int totalRequestsToPool()
```

Retrieves the total number of requests that the IBM Data Server Driver for JDBC and SQLJ has made to the pool since the pool was created.

totalTimeBlocked
Format:

```
public abstract long totalTimeBlocked()
```

Retrieves the total time in milliseconds for requests that were blocked by the pool. This time can be much larger than the elapsed execution time of the application if the application uses multiple threads.

DB2PreparedStatement interface

The `com.ibm.db2.jcc.DB2PreparedStatement` interface extends the `com.ibm.db2.jcc.DB2Statement` and `java.sql.PreparedStatement` interfaces.

DB2PreparedStatement fields

The following constants are defined only for the IBM Data Server Driver for JDBC and SQLJ.

public static DBIndicatorDefault DB_PARAMETER_DEFAULT
This constant can be used with standard interfaces, such as `PreparedStatement.setObject` or `ResultSet.updateObject` to indicate that the default value is assigned to the associated parameter.

public static DBIndicatorUnassigned DB_PARAMETER_UNASSIGNED
This constant can be used with standard interfaces, such as `PreparedStatement.setObject` or `ResultSet.updateObject` to indicate that the associated parameter is unassigned.

DB2PreparedStatement methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

executeDB2QueryBatch
Format:

```
public void executeDB2QueryBatch()
  throws java.sql.SQLException
```

Executes a statement batch that contains queries with parameters.

This method is not supported for connections to IBM Informix data sources.

getDBGeneratedKeys
Format:

```
public java.sql.ResultSet[] getDBGeneratedKeys()
  throws java.sql.SQLException
```

Retrieves automatically generated keys that were created when INSERT statements were executed in a batch. Each `ResultSet` object that is returned contains the automatically generated keys for a single statement in the batch.

`getDBGeneratedKeys` returns an array of length 0 under the following conditions:

- `getDBGeneratedKeys` is called out of sequence. For example, if `getDBGeneratedKeys` is called before `executeBatch`, an array of length 0 is returned.
- The `PreparedStatement` that is executed in a batch was not created using one of the following methods:

```
Connection.prepareStatement(String sql, int[] autoGeneratedKeys)
Connection.prepareStatement(String sql, String[] autoGeneratedColumnNames)
Connection.prepareStatement(String sql, Statement.RETURN_GENERATED_KEYS)
```

If `getDBGeneratedKeys` is called against a `PreparedStatement` that was created using one of the previously listed methods, and the `PreparedStatement` is not in a batch, a single `ResultSet` is returned.

getEstimateCost
Format:

```
public int getEstimateCost()
  throws java.sql.SQLException
```

Returns the estimated cost of an SQL statement from the data server after the data server dynamically prepares the statement successfully. This value is the same as the fourth element in the sqlerrd array of the SQLCA.

If the deferPrepares property is set to `true`, calling `getEstimateCost` causes the data server to execute a dynamic prepare operation.

If the SQL statement cannot be prepared, or the data server does not return estimated cost information at prepare time, `getEstimateCost` returns -1.

getEstimateRowCount

Format:

```
public int getEstimateRowCount()
  throws java.sql.SQLException
```

Returns the estimated row count for an SQL statement from the data server after the data server dynamically prepares the statement successfully. This value is the same as the third element in the sqlerrd array of the SQLCA.

If the deferPrepares property is set to `true`, calling `getEstimateRowCount` causes the data server to execute a dynamic prepare operation.

If the SQL statement cannot be prepared, or the data server does not return estimated row count information at prepare time, `getEstimateRowCount` returns -1.

setDB2BlobFileReference

Format:

```
public void setDB2BlobFileReference(int parameterIndex,
  com.ibm.db2.jcc.DB2BlobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a BLOB file reference variable value to a parameter.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS.

Parameters:

parameterIndex
The index of the parameter marker to which a file reference variable value is assigned.

fileRef
The `com.ibm.db2.jcc.DB2BlobFileReference` value that is assigned to the parameter marker.

setDB2ClobFileReference

Format:

```
public void setDB2ClobFileReference(int parameterIndex,
  com.ibm.db2.jcc.DB2ClobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a CLOB file reference variable value to a parameter.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS.

Parameters:

parameterIndex
The index of the parameter marker to which a file reference variable value is assigned.

fileRef
The `com.ibm.db2.jcc.DB2ClobFileReference` value that is assigned to the parameter marker.

setDB2XmlAsBlobFileReference

Format:

```
public void setDB2XmlAsBlobFileReference(int parameterIndex,
  com.ibm.db2.jcc.DB2XmlAsBlobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a XML AS BLOB file reference variable value to a parameter.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS.

Parameters:

parameterIndex
The index of the parameter marker to which a file reference variable value is assigned.

fileRef
The `com.ibm.db2.jcc.DB2XmlAsBlobFileReference` value that is assigned to the parameter marker.

setDB2XmlAsClobFileReference

Format:

```
public void setDB2XmlAsClobFileReference(int parameterIndex,
  com.ibm.db2.jcc.DB2XmlAsClobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a XML AS CLOB file reference variable value to a parameter.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS.

Parameters:

parameterIndex
The index of the parameter marker to which a file reference variable value is assigned.

fileRef
The `com.ibm.db2.jcc.DB2XmlAsClobFileReference` value that is assigned to the parameter marker.

setDBTimestamp

Format:

```
public void setDBTimestamp(int parameterIndex,
  DBTimestamp timestamp)
  throws java.sql.SQLException
```

Assigns a `DBTimestamp` value to a parameter.

Parameters:

parameterIndex
The index of the parameter marker to which a `DBTimestamp` variable value is assigned.

timestamp
The `DBTimestamp` value that is assigned to the parameter marker.

This method is not supported for connections to IBM Informix data sources.

setJccArrayAtName

Format:

```
public void setJccArrayAtName(String parameterMarkerName,
  java.sql.Array x)
  throws java.sql.SQLException
```

Assigns a `java.sql.Array` value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The java.sql.Array value that is assigned to the named parameter marker.

setJccAsciiStreamAtName
Formats:

Supported by the IBM Data Server Driver for JDBC and SQLJ version 3.57 and later:

```
public void setJccAsciiStreamAtName(String parameterMarkerName,
  java.io.InputStream x, int length)
  throws java.sql.SQLException
```

Supported by the IBM Data Server Driver for JDBC and SQLJ version 4.7 and later:

```
public void setJccAsciiStreamAtName(String parameterMarkerName,
  java.io.InputStream x)
  throws java.sql.SQLException
public void setJccAsciiStreamAtName(String parameterMarkerName,
  java.io.InputStream x, long length)
  throws java.sql.SQLException
```

Assigns an ASCII value in a java.io.InputStream to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The ASCII java.io.InputStream value that is assigned to the parameter marker.

length
The length in bytes of the java.io.InputStream value that is assigned to the named parameter marker.

setJccBigDecimalAtName
Format:

```
public void setJccBigDecimalAtName(String parameterMarkerName,
  java.math.BigDecimal x)
  throws java.sql.SQLException
```

Assigns a java.math.BigDecimal value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The java.math.BigDecimal value that is assigned to the named parameter marker.

setJccBinaryStreamAtName
Formats:

Supported by the IBM Data Server Driver for JDBC and SQLJ version 3.57 and later:

```
public void setJccBinaryStreamAtName(String parameterMarkerName,
  java.io.InputStream x, int length)
  throws java.sql.SQLException
```

Supported by the IBM Data Server Driver for JDBC and SQLJ version 4.7 and later:

```
public void setJccBinaryStreamAtName(String parameterMarkerName,
  java.io.InputStream x)
  throws java.sql.SQLException
public void setJccBinaryStreamAtName(String parameterMarkerName,
  java.io.InputStream x, long length)
  throws java.sql.SQLException
```

Assigns a binary value in a `java.io.InputStream` to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The binary `java.io.InputStream` value that is assigned to the parameter marker.

length
The number of bytes of the `java.io.InputStream` value that are assigned to the named parameter marker.

setJccBlobAtName
Formats:

Supported by the IBM Data Server Driver for JDBC and SQLJ version 3.57 and later:

```
public void setJccBlobAtName(String parameterMarkerName,
  java.sql.Blob x)
  throws java.sql.SQLException
```

Supported by the IBM Data Server Driver for JDBC and SQLJ version 4.7 and later:

```
public void setJccBlobAtName(String parameterMarkerName,
  java.io.InputStream x)
  throws java.sql.SQLException
public void setJccBlobAtName(String parameterMarkerName,
  java.io.InputStream x, long length)
  throws java.sql.SQLException
```

Assigns a BLOB value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The `java.sql.Blob` value or `java.io.InputStream` value that is assigned to the parameter marker.

length
The number of bytes of the `java.io.InputStream` value that are assigned to the named parameter marker.

setJccBooleanAtName
Format:

```
public void setJccBooleanAtName(String parameterMarkerName,
  boolean x)
  throws java.sql.SQLException
```

Assigns a boolean value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The boolean value that is assigned to the named parameter marker.

setJccByteAtName
Format:

```
public void setJccByteAtName(String parameterMarkerName,
  byte x)
  throws java.sql.SQLException
```

Assigns a byte value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The byte value that is assigned to the named parameter marker.

setJccBytesAtName
Format:

```
public void setJccBytesAtName(String parameterMarkerName,
  byte[] x)
  throws java.sql.SQLException
```

Assigns an array of byte values to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The byte array that is assigned to the named parameter marker.

setJccCharacterStreamAtName
Formats:

Supported by the IBM Data Server Driver for JDBC and SQLJ version 3.57 and later:

```
public void setJccCharacterStreamAtName(String parameterMarkerName,
  java.io.Reader x, int length)
  throws java.sql.SQLException
```

Supported by the IBM Data Server Driver for JDBC and SQLJ version 4.7 and later:

```
public void setJccCharacterStreamAtName(String parameterMarkerName,
  java.io.Reader x)
```

```
  throws java.sql.SQLException
public void setJccCharacterStreamAtName(String parameterMarkerName,
  java.io.Reader x, long length)
  throws java.sql.SQLException
```

Assigns a Unicode value in a `java.io.Reader` to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The Unicode `java.io.Reader` value that is assigned to the named parameter marker.

length
The number of characters of the `java.io.InputStream` value that are assigned to the named parameter marker.

setJccClobAtName
Formats:

Supported by the IBM Data Server Driver for JDBC and SQLJ version 3.57 and later:

```
public void setJccClobAtName(String parameterMarkerName,
  java.sql.Clob x)
  throws java.sql.SQLException
```

Supported by the IBM Data Server Driver for JDBC and SQLJ version 4.7 and later:

```
public void setJccClobAtName(String parameterMarkerName,
  java.io.Reader x)
  throws java.sql.SQLException
public void setJccClobAtName(String parameterMarkerName,
  java.io.Reader x, long length)
  throws java.sql.SQLException
```

Assigns a CLOB value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The `java.sql.Clob` value or `java.io.Reader` value that is assigned to the named parameter marker.

length
The number of bytes of the `java.io.InputStream` value that are assigned to the named parameter marker.

setJccDateAtName
Formats:

```
public void setJccDateAtName(String parameterMarkerName,
  java.sql.Date x)
  throws java.sql.SQLException
public void setJccDateAtName(String parameterMarkerName,
  java.sql.Date x,
  java.util.Calendar cal)
  throws java.sql.SQLException
```

Assigns a java.sql.Date value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The java.sql.Date value that is assigned to the named parameter marker.

cal
The java.util.Calendar object that the IBM Data Server Driver for JDBC and SQLJ uses to construct the date.

setJccDB2BlobFileReferenceAtName
Format:

```
public void setJccDB2BlobFileReferenceAtName(int parameterMarkerName,
  com.ibm.db2.jcc.DB2BlobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a BLOB file reference variable value to a named parameter marker.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a file reference variable value is assigned.

fileRef
The com.ibm.db2.jcc.DB2BlobFileReference value that is assigned to the named parameter marker.

setJccDB2ClobFileReferenceAtName
Format:

```
public void setJccDB2ClobFileReferenceAtName(int parameterMarkerName,
  com.ibm.db2.jcc.DB2ClobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a CLOB file reference variable value to a named parameter marker.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a file reference variable value is assigned.

fileRef
The com.ibm.db2.jcc.DB2ClobFileReference value that is assigned to the named parameter marker.

setJccDB2XmlAsBlobFileReferenceAtName
Format:

```
public void setJccDB2XmlAsBlobFileReferenceAtName(String parameterMarkerName,
  com.ibm.db2.jcc.DB2XmlAsBlobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a XML AS BLOB file reference variable value to a named parameter marker.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS Version 9 or later.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a file reference variable value is assigned.

fileRef
The com.ibm.db2.jcc.DB2XmlAsBlobFileReference value that is assigned to the named parameter marker.

setJccDB2XmlAsClobFileReferenceAtName
Format:

```
public void setJccDB2XmlAsClobFileReferenceAtName(int parameterMarkerName,
  com.ibm.db2.jcc.DB2XmlAsClobFileReference fileRef)
  throws java.sql.SQLException
```

Assigns a XML AS CLOB file reference variable value to a named parameter marker.

This method applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS Version 9 or later.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a file reference variable value is assigned.

fileRef
The com.ibm.db2.jcc.DB2XmlAsClobFileReference value that is assigned to the named parameter marker.

setJccDBTimestampAtName
Format:

```
public void setJccDBTimestampAtName(String parameterMarkerName,
  DBTimestamp timestamp)
  throws java.sql.SQLException
```

Assigns a DBTimestamp value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a DBTimestamp variable value is assigned.

timestamp
The DBTimestamp value that is assigned to the named parameter marker.

This method is not supported for connections to IBM Informix data sources.

setJccDBDefaultAtName
Formats:

```
public void setJccDBDefaultAtName(String parameterMarkerName)
  throws SQLException
```

Assigns the default value to a named parameter marker. Execution of setJccDBDefaultAtName produces the same results as using the literal DEFAULT in the SQL string, instead of the parameter marker name.

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

This method is not supported for connections to IBM Informix data sources.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

setJccDBUnassignedAtName
Formats:

```
public void setJccDBUnassignedAtName(String parameterMarkerName)
  throws SQLException
```

Does not assign a value to the specified named parameter. Execution of setJccDBUnassignedAtName produces the same result as if the specified parameter marker name had not appeared in the SQL string.

Parameters:

parameterMarkerName
The name of the parameter marker whose value is to be unassigned.

This method is not supported for connections to IBM Informix data sources.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

setJccDoubleAtName
Format:

```
public void setJccDoubleAtName(String parameterMarkerName,
  double x)
  throws java.sql.SQLException
```

Assigns a value of type double to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value of type double that is assigned to the parameter marker.

setJccFloatAtName
Format:

```
public void setJccFloatAtName(String parameterMarkerName,
  float x)
  throws java.sql.SQLException
```

Assigns a value of type float to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value of type float that is assigned to the parameter marker.

setJccIntAtName
Format:

```
public void setJccIntAtName(String parameterMarkerName,
  int x)
  throws java.sql.SQLException
```

Assigns a value of type int to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value of type int that is assigned to the parameter marker.

setJccLongAtName
Format:

```
public void setJccLongAtName(String parameterMarkerName,
  long x)
  throws java.sql.SQLException
```

Assigns a value of type long to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value of type long that is assigned to the parameter marker.

setJccNullAtName
Format:

```
public void setJccNullAtName(String parameterMarkerName,
  int jdbcType)
  throws java.sql.SQLException
public void setJccNullAtName(String parameterMarkerName,
  int jdbcType,
  String typeName)
  throws java.sql.SQLException
```

Assigns the SQL NULL value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

jdbcType
The JDBC type code of the NULL value that is assigned to the parameter marker, as defined in `java.sql.Types`.

typeName
If *jdbcType* is `java.sql.Types.DISTINCT` or `java.sql.Types.REF`, the fully-qualified name of the SQL user-defined type of the NULL value that is assigned to the parameter marker.

setJccObjectAtName

Formats:

```
public void setJccObjectAtName(String parameterMarkerName,
  java.sql.Object x)
  throws java.sql.SQLException
public void setJccObjectAtName(String parameterMarkerName,
  java.sql.Object x,
  int targetJdbcType)
  throws java.sql.SQLException
public void setJccObjectAtName(String parameterMarkerName,
  java.sql.Object x,
  int targetJdbcType,
  int scale)
  throws java.sql.SQLException
```

Assigns a value with type `java.lang.Object` to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value with type Object that is assigned to the parameter marker.

targetJdbcType
The data type, as defined in `java.sql.Types`, that is assigned to the input value when it is sent to the data source.

scale
The scale of the value that is assigned to the parameter marker. This parameter applies only to these cases:

- If *targetJdbcType* is `java.sql.Types.DECIMAL` or `java.sql.Types.NUMERIC`, *scale* is the number of digits to the right of the decimal point.
- If *x* has type `java.io.InputStream` or `java.io.Reader`, *scale* is the this is the length of the data in the `Stream` or `Reader` object.

setJccShortAtName

Format:

```
public void setJccShortAtName(String parameterMarkerName,
  short x)
  throws java.sql.SQLException
```

Assigns a value of type short to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to `DB2BaseDataSource.YES` (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value of type short that is assigned to the parameter marker.

setJccSQLXMLAtName

Format:

```
public void setJccSQLXMLAtName(String parameterMarkerName,
  java.sql.SQLXML x)
  throws java.sql.SQLException
```

Assigns a value of type `java.sql.SQLXML` to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

This method is supported only for connections to Db2 on Linux, UNIX, and Windows systems Version 9.1 or later or Db2 for z/OS Version 9 or later.

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value of type java.sql.SQLXML that is assigned to the parameter marker.

setJccStringAtName
Format:

```
public void setJccStringAtName(String parameterMarkerName,
  String x)
  throws java.sql.SQLException
```

Assigns a value of type String to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The value of type String that is assigned to the parameter marker.

setJccTimeAtName
Formats:

```
public void setJccTimeAtName(String parameterMarkerName,
  java.sql.Time x)
  throws java.sql.SQLException
public void setJccTimeAtName(String parameterMarkerName,
  java.sql.Time x,
  java.util.Calendar cal)
  throws java.sql.SQLException
```

Assigns a java.sql.Time value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The java.sql.Time value that is assigned to the parameter marker.

cal
The java.util.Calendar object that the IBM Data Server Driver for JDBC and SQLJ uses to construct the time.

setJccTimestampAtName
Formats:

```
public void setJccTimestampAtName(String parameterMarkerName,
  java.sql.Timestamp x)
  throws java.sql.SQLException
public void setJccTimestampAtName(String parameterMarkerName,
  java.sql.Timestamp x,
```

```
  java.util.Calendar cal)
  throws java.sql.SQLException
```

Assigns a java.sql.Timestamp value to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The java.sql.Timestamp value that is assigned to the parameter marker.

cal
The java.util.Calendar object that the IBM Data Server Driver for JDBC and SQLJ uses to construct the timestamp.

setJccUnicodeStreamAtName
Format:

```
public void setJccUnicodeStreamAtName(String parameterMarkerName,
  java.io.InputStream x, int length)
  throws java.sql.SQLException
```

Assigns a Unicode value in a java.io.InputStream to a named parameter marker.

This method can be called only if the enableNamedParameterMarkers property is set to DB2BaseDataSource.YES (1).

Parameters:

parameterMarkerName
The name of the parameter marker to which a value is assigned.

x
The Unicode java.io.InputStream value that is assigned to the parameter marker.

length
The number of bytes of the java.io.InputStream value that are assigned to the parameter marker.

setDBDefault
Formats:

```
public void setDBDefault(int parameterIndex)
  throws SQLException
```

Assigns the default value to the specified parameter. Execution of setDBDefault produces the same results as using the literal DEFAULT in the SQL string, instead of the parameter.

Parameters:

parameterIndex
The number of the parameter whose value is being updated.

This method is not supported for connections to IBM Informix data sources.

setDBUnassigned
Formats:

```
public void setDBUnassigned(int parameterIndex)
  throws SQLException
```

Does not assign a value to the specified parameter. Execution of setDBUnassigned produces the same result as if the specified parameter had not appeared in the SQL string.

Parameters:

parameterIndex
The number of the parameter whose value is to be unassigned.

This method is not supported for connections to IBM Informix data sources.

Related tasks

"Making batch queries in JDBC applications" on page 40
The IBM Data Server Driver for JDBC and SQLJ provides a IBM Data Server Driver for JDBC and SQLJ-only `DB2PreparedStatement` interface that lets you perform batch queries on a homogeneous batch.

DB2ResultSet interface

The `com.ibm.db2.jcc.DB2ResultSet` interface is used to create objects from which IBM Data Server Driver for JDBC and SQLJ-only query information can be obtained.

`DB2ResultSet` implements the `java.sql.Wrapper` interface.

DB2ResultSet fields

The following fields are defined only for the IBM Data Server Driver for JDBC and SQLJ.

The integer constants in the following table are used in the column descriptor information that `getDBRowDescriptor` returns. These constants contain information about the column values that are returned by `getDBRowAsBytes`. All fields are defined as `public static int`.

Field value	Description of returned data
REPRESENTATION_FIXED_STRING (0)	Fixed-length string data
REPRESENTATION_BIG_ENDIAN (1)	Signed binary format in which the most significant byte is stored in the highest address
REPRESENTATION_LITTLE_ENDIAN (2)	Signed binary format in which the least significant byte is stored in the highest address
REPRESENTATION_VARIABLE_STRING (2)	String data that begins with a two-byte length field
REPRESENTATION_NUL_TERMINATED_STRING (3)	Nul-terminated string data
REPRESENTATION_FIXED_BYTES (4)	Fixed-length byte string
REPRESENTATION_VARIABLE_BYTES (5)	Byte string that begins with a two-byte length field
REPRESENTATION_NUL_TERMINATED_BYTES (7)	Nul-terminated byte data
REPRESENTATION_FIXED_BINARY (15)	Fixed-length binary string
REPRESENTATION_VARIABLE_BINARY (16)	Binary string that begins with a two-byte length field
REPRESENTATION_PACKED_DECIMAL (48)	Nul-terminated binary string
REPRESENTATION_NUMERIC_CHARACTER (50)	Character-based, fixed-point format
REPRESENTATION_ZONED_DECIMAL (51)	Zoned-decimal format that is returned by IBM System i® and IBM Z
REPRESENTATION_COBOL2_ZONED_DECIMAL (53)	Zoned-decimal format that is returned by Windows or UNIX systems
REPRESENTATION_HEXADECIMAL_FLOATING_POINT (64)	S/390® hexadecimal floating point format
REPRESENTATION_DECIMAL_FLOATING_POINT (66)	Decimal floating point format
REPRESENTATION_IEEE_754_FLOATING_POINT_BYTE_REVERSED (71)	IEEE floating-point format in which the least significant byte is stored in the highest address
REPRESENTATION_IEEE_754_FLOATING_POINT (72)	IEEE floating-point format in which the most significant byte is stored in the highest address

DB2ResultSet methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getDB2RowChangeToken

Format:

```
public long DB2ResultSet.getDB2RowChangeToken()
  throws java.sql.SQLException
```

Returns the row change token for the current row, if it is available. Returns 0 if optimistic locking columns were not requested or are not available.

This method applies only to connections to Db2 on Linux, UNIX, and Windows systems.

getDB2RID

Format:

```
public Object DB2ResultSet.getDB2RID()
  throws java.sql.SQLException
```

Returns the RID for the current row, if it is available. The RID is available if optimistic locking columns were requested and are available. Returns null if optimistic locking columns were not requested or are not available.

This method applies only to connections to Db2 on Linux, UNIX, and Windows systems.

getDB2RIDType

Format:

```
public int DB2ResultSet.getDB2RIDType()
  throws java.sql.SQLException
```

Returns the data type of the RID column in a `DB2ResultSet`. The returned value maps to a `java.sql.Types` constant. If the `DB2ResultSet` does not contain a RID column, `java.sql.Types.NULL` is returned.

This method applies only to connections to Db2 on Linux, UNIX, and Windows systems.

getDBRowDataAsBytes

Format:

```
public Object [] getDBRowDataAsBytes()
  throws SQLException
```

Returns an `Object` array that represents the data in the current row of an open `ResultSet` object.

This method does not apply to connections to IBM Informix.

`getDBRowDataAsBytes` cannot be called if the `ResultSet` object on which it operates meets any of the following conditions:

- A `ResultSet` row that is being retrieved has been updated, deleted, or inserted.
- The `ResultSet` object was created for optimistic locking.

The returned information includes:

- The data in raw byte array format
- The offset to the data for each column

Suppose that `obj` is an instance of the returned `Object` array. The format of the `Object` array is:

obj[0]
A byte array that describes the row data.

obj[1]
An integer array that contains the offset into `obj[0]` of each column description. The offsets can be used to determine the length of the data that is returned for each column. That length represents the length of the raw data, and not the defined length of the column.

If a `ResultSet` object contains a column of any of the following types, the offset value for that column value in obj[1] is -1. -1 indicates that a value for that column is not returned.

- BLOB
- CLOB
- DBCLOB
- XML

The byte array in `obj[0]` has the following format:

```
rnndd...dd...nndd...dd
```

There is one *nndd...dd* set for each column in the row.

The following table describes the contents of the row data:

Item	Description
r	A single byte that has one of the following values: **0** The row data is not valid. One reason for invalid data is that the row has not yet been fetched. **1** The row data is valid.
nn	A two-byte NULL indicator for a column value. Possible values are: **-1** The column value that follows is null. **0** The column value that follows is not null.
dd...dd	Raw byte data for a column value.

getDBRowDescriptor

Format:

```
public int [] getDBRowDescriptor()
  throws SQLException
```

Returns an `int` array that contains descriptive information about each column of the row data that is returned by `getDBRowDataAsBytes`.

This method does not apply to connections to IBM Informix.

Suppose that returnedInfo is an instance of the array that is returned by `getDBRowDescriptor`. The format of the returned array is:

returnedInfo[0]
The number of columns in the row data. Suppose that this value is *n*.

returnedInfo[1] through returnedInfo[*4*n*]
n repeating groups of four integer values. Each group contains descriptive information for a single column. That information is:

Column descriptor number	Description
1	The data type of the column, expressed as an SQLTYPE value. This value is the same as the SQLTYPE value that is returned in an SQLDA.

Column descriptor number	Description
2	The CCSID of the column, for a character data type. For a DECIMAL data type, this value is the scale of the column.
3	The defined length of the column, for all data types except DECIMAL. For a DECIMAL data type, this value is the precision of the column. For varying-length character data types, this value might be greater than the number of returned bytes.
4	Additional information about the column. Possible values are described in "DB2ResultSet fields" on page 462.

getDBTimestamp

Formats:

```
public DBTimestamp getDBTimestamp(int parameterIndex)
  throws SQLException
public DBTimestamp getDBTimestamp(String parameterName)
  throws SQLException
```

Returns the value in the current row of a TIMESTAMP or TIMESTAMP WITH TIME ZONE column that is in a `DB2ResultSet` object as a `DBTimestamp` object. For a TIMESTAMP column, the returned value has the local time zone. If the value of the `DB2ResultSet` column is NULL, the returned value is null.

Parameters:

parameterIndex
The number of the column in the `DB2ResultSet` whose value is being retrieved.

parameterName
The name of the column in the `DB2ResultSet` whose value is being retrieved.

setMAXBLKEXT

Formats:

```
public void setMAXBLKEXT(int maxblkext)
  throws SQLException
```

Specifies the maximum number of extra blocks that the DRDA client can receive from the data server without further prompting.

Parameters:

maxblkext
The number of extra blocks to be returned. Possible values are:

-1
The data server determines the maximum number of extra blocks that the client can receive. -1 is the default.

0
The client receives no extra blocks.

n
The maximum number of extra blocks that the client can receive. *n* is an integer that is greater than or equal to 1 and less than or equal to 100.

The MAXBLKEXT value that is set through this method overrides the value of the MAXBLKEXT `Connection` or `DataSource` property.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems.

updateDBDefault

Formats:

```
public void updateDBDefault(int parameterIndex)
  throws SQLException
public void updateDBDefault(String columnName)
  throws SQLException
```

Assigns the default value to the specified column in a DB2ResultSet object. This method does not update the underlying table.

Parameters:

parameterIndex
The number of the column in the DB2ResultSet whose value is being updated.

columnName
The name of the column in the DB2ResultSet whose value is being updated.

This method is not supported for connections to IBM Informix data sources.

DB2ResultSetMetaData interface

The com.ibm.db2.jcc.DB2ResultSetMetaData interface provides methods that provide information about a ResultSet object.

Before a com.ibm.db2.jcc.DB2ResultSetMetaData method can be used, a java.sql.ResultSetMetaData object that is returned from a java.sql.ResultSet.getMetaData call needs to be cast to com.ibm.db2.jcc.DB2ResultSetMetaData.

DB2ResultSetMetaData methods:

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getDBTemporalColumnType

Format:

```
public int getDBTemporalColumnType (int column)
  throws java.sql.SQLException
```

Returns:

-1
If *column* is not a ROW BEGIN, ROW END or TRANSACTION START ID column.

1
If *column* is a ROW BEGIN column.

2
If *column* is a ROW END column.

3
If *column* is a TRANSACTION START ID column.

Parameter descriptions:

column
The ordinal position of a column in the ResultSet.

getMaxStringUnitBits

Format:

```
public int getMaxStringUnitBits (int column)
  throws java.sql.SQLException
```

Returns the maximum number of bits in a string unit for single-byte and double-byte character data types. The value that is returned is:

8
For a character column that is defined with OCTETS.

16
For a character column that is defined with CODEUNITS16.

32
For a character column that is defined with CODEUNITS32.

Parameter descriptions:

column
The ordinal position of a column in the `ResultSet`.

This method applies only to connections to Db2 on Linux, UNIX, and Windows systems Version 10.5 or later data servers.

isDB2ColumnNameDerived
Format:

```
public boolean isDB2ColumnNameDerived (int column)
  throws java.sql.SQLException
```

Returns `true` if the name of a `ResultSet` column is in the SQL SELECT list that generated the `ResultSet`.

For example, suppose that a `ResultSet` is generated from the SQL statement SELECT EMPNAME, SUM(SALARY) FROM EMP. Column name EMPNAME is derived from the SQL SELECT list, but the name of the column in the `ResultSet` that corresponds to SUM(SALARY) is not derived from the SELECT list.

Parameter descriptions:

column
The ordinal position of a column in the `ResultSet`.

DB2RowID interface

The `com.ibm.db2.jcc.DB2RowID` interface is used for declaring Java objects for use with the SQL ROWID data type.

The `com.ibm.db2.jcc.DB2RowID` interface does not apply to connection to IBM Informix.

DB2RowID methods

The following method is defined only for the IBM Data Server Driver for JDBC and SQLJ.

getBytes
Format:

```
public byte[] getBytes()
```

Converts a com.ibm.jcc.DB2RowID object to bytes.

Related concepts
“ROWIDs in SQLJ with the IBM Data Server Driver for JDBC and SQLJ” on page 159
Db2 for z/OS and Db2 for IBM i support the ROWID data type for a column in a table. A ROWID is a value that uniquely identifies a row in a table.

“ROWIDs in JDBC with the IBM Data Server Driver for JDBC and SQLJ” on page 61

Db2 for z/OS and Db2 for IBM i support the ROWID data type for a column in a database table. A ROWID is a value that uniquely identifies a row in a table.

DB2SimpleDataSource class

The `com.ibm.db2.jcc.DB2SimpleDataSource` class extends the `DB2BaseDataSource` class.

A `DB2SimpleDataSource` object does not support connection pooling or distributed transactions. It contains all of the properties and methods that the `DB2BaseDataSource` class contains.

`DB2SimpleDataSource` implements the `java.sql.Wrapper` interface.

DB2SimpleDataSource methods

The following method is defined only for the IBM Data Server Driver for JDBC and SQLJ.

setPassword

Format:

```
public synchronized void setPassword(String password)
```

Sets the password for the `DB2SimpleDataSource` object. There is no corresponding `getPassword` method. Therefore, the password cannot be encrypted because there is no way to retrieve the password so that you can decrypt it.

Related tasks

“Creating and deploying DataSource objects” on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

“Connecting to a data source using the DataSource interface” on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

“Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products” on page 224
Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

DB2Sqlca class

The `com.ibm.db2.jcc.DB2Sqlca` class is an encapsulation of the SQLCA.

DB2Sqlca methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getMessage

Format:

```
public abstract String getMessage()
```

Returns error message text.

getSqlCode

Format:

```
public abstract int getSqlCode()
```

Returns an SQL error code value.

getSqlErrd

Format:

```
public abstract int[] getSqlErrd()
```

Returns an array, each element of which contains an SQLCA SQLERRD.

getSqlErrmc
Format:

```
public abstract String getSqlErrmc()
```

Returns a string that contains the SQLCA SQLERRMC values, delimited with spaces.

getSqlErrmcTokens
Format:

```
public abstract String[] getSqlErrmcTokens()
```

Returns an array, each element of which contains an SQLCA SQLERRMC token.

getSqlErrp
Format:

```
public abstract String getSqlErrp()
```

Returns the SQLCA SQLERRP value.

getSqlState
Format:

```
public abstract String getSqlState()
```

Returns the SQLCA SQLSTATE value.

getSqlWarn
Format:

```
public abstract char[] getSqlWarn()
```

Returns an array, each element of which contains an SQLCA SQLWARN value.

Related tasks

“Handling SQL warnings in an SQLJ application” on page 173
Other than a +100 SQL error code on a SELECT INTO statement, warnings from the data server do not throw SQLExceptions. To handle warnings from the data server, you need to give the program access to the `java.sql.SQLWarning` class.

“Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ” on page 111
As in all Java programs, error handling for JDBC applications is done using `try/catch` blocks. Methods throw exceptions when an error occurs, and the code in the `catch` block handles those exceptions.

Related reference

Description of SQLCA fields (Db2 SQL)

DB2Statement interface

The `com.ibm.db2.jcc.DB2Statement` interface extends the `java.sql.Statement` interface.

`DB2Statement` implements the `java.sql.Wrapper` interface.

DB2Statement methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getAffectedRowCount
Format:

```
public int getAffectedRowCount()
  throws java.sql.SQLException
```

Returns the number of rows that are affected by successful execution of an SQL statement. If the SQL statement is INSERT, UPDATE, or DELETE, `getAffectedRowCount` returns the same value that is returned by `java.sql.Statement.getUpdateCount`.

The value that is returned by `getAffectedRowCount` is the same information that is returned by the data server in the SQLCA after successful execution of an SQL statement.

getDB2ClientProgramId

Format:

```
public String getDB2ClientProgramId()
  throws java.sql.SQLException
```

Returns the user-defined client program identifier for the connection, which is stored on the data source.

getDB2ClientProgramId does not apply to Db2 on Linux, UNIX, and Windows systems data servers.

setDB2ClientProgramId

Format:

```
public abstract void setDB2ClientProgramId(String program-ID)
  throws java.sql.SQLException
```

Sets a user-defined program identifier for the connection on a data server. That program identifier is an 80-byte string that is used to identify the caller.

setDB2ClientProgramId does not apply to Db2 on Linux, UNIX, and Windows systems data servers.

The Db2 for z/OS server places the string in IFCID 316 trace records along with other statistics, so that you can identify which program is associated with a particular SQL statement.

getIDSBigSerial

Format:

```
public int getIDSBigSerial()
  throws java.sql.SQLException
```

Retrieves an automatically generated key from a BIGSERIAL column after the automatically generated key was inserted by a previously executed INSERT statement.

The following conditions must be true for `getIDSBigSerial` to execute successfully:

- The INSERT statement is the last SQL statement that is executed before this method is called.
- The table into which the row is inserted contains a BIGSERIAL column.
- The form of the JDBC `Connection.prepareStatement` method or `Statement.executeUpdate` method that prepares or executes the INSERT statement does not have parameters that request automatically generated keys.

This method applies only to connections to IBM Informix databases.

getIDSSerial

Format:

```
public int getIDSSerial()
  throws java.sql.SQLException
```

Retrieves an automatically generated key from a SERIAL column after the automatically generated key was inserted by a previously executed INSERT statement.

The following conditions must be true for `getIDSSerial` to execute successfully:

- The INSERT statement is the last SQL statement that is executed before this method is called.

- The table into which the row is inserted contains a SERIAL column.
- The form of the JDBC `Connection.prepareStatement` method or `Statement.executeUpdate` method that prepares or executes the INSERT statement does not have parameters that request automatically generated keys.

This method applies only to connections to IBM Informix databases.

getIDSSerial8

Format:

```
public long getIDSSerial8()
  throws java.sql.SQLException
```

Retrieves an automatically generated key from a SERIAL8 column after the automatically generated key was inserted by a previously executed INSERT statement.

The following conditions must be true for `getIDSSerial8` to execute successfully:

- The INSERT statement is the last SQL statement that is executed before this method is called.
- The table into which the row is inserted contains a SERIAL8 column.
- The form of the JDBC `Connection.prepareStatement` method or `Statement.executeUpdate` method that prepares or executes the INSERT statement does not have parameters that request automatically generated keys.

This method applies only to connections to IBM Informix data sources.

getIDSSQLStatementOffSet

Format:

```
public int getIDSSQLStatementOffSet()
  throws java.sql.SQLException
```

After an SQL statement executes on an IBM Informix data source, if the statement has a syntax error, getIDSSQLStatementOffSet returns the offset into the statement text of the syntax error.

getIDSSQLStatementOffSet returns:

- 0, if the statement does not have a syntax error.
- -1, if the data source is not IBM Informix.

This method applies only to connections to IBM Informix data sources.

setMAXBLKEXT

Formats:

```
public void setMAXBLKEXT(int maxblkext)
  throws SQLException
```

Specifies the maximum number of extra blocks that the DRDA client can receive from the data server without further prompting.

Parameters:

maxblkext

The number of extra blocks to be returned. Possible values are:

-1

The data server determines the maximum number of extra blocks that the client can receive. -1 is the default.

0

The client receives no extra blocks.

n

The maximum number of extra blocks that the client can receive. *n* is an integer that is greater than or equal to 1 and less than or equal to 100.

The MAXBLKEXT value that is set through this method overrides the value of the MAXBLKEXT `Connection` or `DataSource` property.

This property is applicable only to IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems.

Related reference

"DB2PreparedStatement interface" on page 448
The `com.ibm.db2.jcc.DB2PreparedStatement` interface extends the `com.ibm.db2.jcc.DB2Statement` and `java.sql.PreparedStatement` interfaces.

DB2SystemMonitor interface

The `com.ibm.db2.jcc.DB2SystemMonitor` interface is used for collecting system monitoring data for a connection. Each connection can have one `DB2SystemMonitor` instance.

DB2SystemMonitor fields

The following fields are defined only for the IBM Data Server Driver for JDBC and SQLJ.

public final static int RESET_TIMES
public final static int ACCUMULATE_TIMES
These values are arguments for the `DB2SystemMonitor.start` method. RESET_TIMES sets time counters to zero before monitoring starts. ACCUMULATE_TIMES does not set time counters to zero.

DB2SystemMonitor methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

enable
Format:

```
public void enable(boolean on)
  throws java.sql.SQLException
```

Enables the system monitor that is associated with a connection. This method cannot be called during monitoring. All times are reset when `enable` is invoked.

getApplicationTimeMillis
Format:

```
public long getApplicationTimeMillis()
  throws java.sql.SQLException
```

Returns the sum of the application, JDBC driver, network I/O, and database server elapsed times. The time is in milliseconds.

A monitored elapsed time interval is the difference, in milliseconds, between these points in the JDBC driver processing:

Interval beginning
When `start` is called.

Interval end
When `stop` is called.

`getApplicationTimeMillis` returns 0 if system monitoring is disabled. Calling this method without first calling the `stop` method results in an `SQLException`.

getCoreDriverTimeMicros
Format:

```
public long getCoreDriverTimeMicros()
  throws java.sql.SQLException
```

Returns the sum of elapsed monitored API times that were collected while system monitoring was enabled. The time is in microseconds.

A monitored API is a JDBC driver method for which processing time is collected. In general, elapsed times are monitored only for APIs that might result in network I/O or database server interaction. For example, `PreparedStatement.setXXX` methods and `ResultSet.getXXX` methods are not monitored.

Monitored API elapsed time includes the total time that is spent in the driver for a method call. This time includes any network I/O time and database server elapsed time.

A monitored API elapsed time interval is the difference, in microseconds, between these points in the JDBC driver processing:

Interval beginning
When a monitored API is called by the application.

Interval end
Immediately before the monitored API returns control to the application.

`getCoreDriverTimeMicros` returns 0 if system monitoring is disabled. Calling this method without first calling the `stop` method, or calling this method when the underlying JVM does not support reporting times in microseconds results in an `SQLException`.

getNetworkIOTimeMicros
Format:

```
public long getNetworkIOTimeMicros()
  throws java.sql.SQLException
```

Returns the sum of elapsed network I/O times that were collected while system monitoring was enabled. The time is in microseconds.

Elapsed network I/O time includes the time to write and read DRDA data from network I/O streams. A network I/O elapsed time interval is the time interval to perform the following operations in the JDBC driver:

- Issue a TCP/IP command to send a DRDA message to the database server. This time interval is the difference, in microseconds, between points immediately before and after a write and flush to the network I/O stream is performed.
- Issue a TCP/IP command to receive DRDA reply messages from the database server. This time interval is the difference, in microseconds, between points immediately before and after a read on the network I/O stream is performed.

Network I/O time intervals are captured for all send and receive operations, including the sending of messages for commits and rollbacks.

The time spent waiting for network I/O might be impacted by delays in CPU dispatching at the database server for low-priority SQL requests.

`getNetworkIOTimeMicros` returns 0 if system monitoring is disabled. Calling this method without first calling the `stop` method, or calling this method when the underlying JVM does not support reporting times in microseconds results in an `SQLException`.

getServerTimeMicros
Format:

```
public long getServerTimeMicros()
  throws java.sql.SQLException
```

Returns the sum of all reported database server elapsed times that were collected while system monitoring was enabled. The time is in microseconds.

The database server reports elapsed times under these conditions:

- The database server supports returning elapsed time data to the client.

Db2 on Linux, UNIX, and Windows systems Version 9.5 and later and Db2 for z/OS support this function.

- The database server performs operations that can be monitored. For example, database server elapsed time is not returned for commits or rollbacks.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 on Linux, UNIX, and Windows systems, and IBM Data Server Driver for JDBC and SQLJ type 4 connectivity: The database server elapsed time is defined as the elapsed time to parse the request data stream, process the command, and generate the reply data stream at the database server. Network time to receive or send the data stream is not included. The database server elapsed time interval is the difference, in microseconds, between these points in the database server processing:

Interval beginning
When the operating system dispatches the database server to process a TCP/IP message that is received from the JDBC driver.

Interval end
When the database server is ready to issue the TCP/IP command to return the reply message to the client.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS: The database server elapsed time interval is the difference, in microseconds, between these points in the JDBC driver native processing:

Interval beginning
The z/OS Store Clock (STCK) value when a JDBC driver native method calls the RRS attachment facility to process an SQL request.

Interval end
The z/OS Store Clock (STCK) value when control returns to the JDBC driver native method following an RRS attachment facility call to process an SQL request.

`getServerTimeMicros` returns 0 if system monitoring is disabled. Calling this method without first calling the `stop` method results in an `SQLException`.

start
Format:

```
public void start (int lapMode)
  throws java.sql.SQLException
```

If the system monitor is enabled, `start` begins the collection of system monitoring data for a connection. Valid values for *lapMode* are RESET_TIMES or ACCUMULATE_TIMES.

Calling this method with system monitoring disabled does nothing. Calling this method more than once without an intervening `stop` call results in an `SQLException`.

stop
Format:

```
public void stop()
  throws java.sql.SQLException
```

If the system monitor is enabled, `stop` ends the collection of system monitoring data for a connection. After monitoring is stopped, monitored times can be obtained with the `getXXX` methods of `DB2SystemMonitor`.

Calling this method with system monitoring disabled does nothing. Calling this method without first calling `start`, or calling this method more than once without an intervening `start` call results in an `SQLException`.

Related concepts
“System monitoring for the IBM Data Server Driver for JDBC and SQLJ” on page 645

To assist you in monitoring the performance of your applications with the IBM Data Server Driver for JDBC and SQLJ, the driver provides two methods to collect information for a connection.

DB2TraceManager class

The `com.ibm.db2.jcc.DB2TraceManager` class controls the global log writer.

The global log writer is driver-wide, and applies to all connections. The global log writer overrides any other JDBC log writers. In addition to starting the global log writer, the `DB2TraceManager` class provides the ability to suspend and resume tracing of any type of log writer. That is, the suspend and resume methods of the `DB2TraceManager` class apply to all current and future `DriverManager` log writers, `DataSource` log writers, or IBM Data Server Driver for JDBC and SQLJ-only connection-level log writers.

DB2TraceManager methods

getTraceManager

Format:

```
static public DB2TraceManager getTraceManager()
  throws java.sql.SQLException
```

Gets an instance of the global log writer.

setLogWriter

Formats:

```
public abstract void setLogWriter(String traceDirectory,
  String baseTraceFileName, int traceLevel)
  throws java.sql.SQLException
public abstract void setLogWriter(String traceFile,
  boolean fileAppend, int traceLevel)
  throws java.sql.SQLException
public abstract void setLogWriter(java.io.PrintWriter logWriter,
  int traceLevel)
  throws java.sql.SQLException
```

Enables a global trace. After `setLogWriter` is called, all calls for `DataSource` or `Connection` traces are discarded until `DB2TraceManager.unsetLogWriter` is called.

When `setLogWriter` is called, all future `Connection` or `DataSource` traces are redirected to a trace file or `PrintWriter`, depending on the form of `setLogWriter` that you use. If the global trace is suspended when `setLogWriter` is called, the specified settings take effect when the trace is resumed.

Parameter descriptions:

traceDirectory

Specifies a directory into which global trace information is written. This setting overrides the settings of the traceDirectory and logWriter properties for a `DataSource` or `DriverManager` connection.

When the form of `setLogWriter` with the traceDirectory parameter is used, the JDBC driver sets the traceFileAppend property to `false` when `setLogWriter` is called, which means that the existing log files are overwritten. Each JDBC driver connection is traced to a different file in the specified directory. The naming convention for the files in that directory depends on whether a non-null value is specified for baseTraceFileName:

- If a null value is specified for baseTraceFileName, a connection is traced to a file named traceFile_global_*n*.

  n is the *n*th JDBC driver connection.
- If a non-null value is specified for baseTraceFileName, a connection is traced to a file named *baseTraceFileName*_global_*n*.

  baseTraceFileName is the value of the baseTraceFileName parameter.

n is the *n*th JDBC driver connection.

baseTraceFileName
Specifies the stem for the names of the files into which global trace information is written. The combination of baseTraceFileName and traceDirectory determines the full path name for the global trace log files.

traceFileName
Specifies the file into which global trace information is written. This setting overrides the settings of the traceFile and logWriter properties for a `DataSource` or `DriverManager` connection.

When the form of `setLogWriter` with the traceFileName parameter is used, only one log file is written.

traceFileName can include a directory path.

logWriter
Specifies a character output stream to which all global log records are written.

This value overrides the logWriter property on a `DataSource` or `DriverManager` connection.

traceLevel
Specifies what to trace.

You can specify one or more of the following traces with the traceLevel parameter:

- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_NONE` (X'00')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTION_CALLS` (X'01')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_STATEMENT_CALLS` (X'02')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_CALLS` (X'04')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRIVER_CONFIGURATION` (X'10')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTS` (X'20')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS` (X'40')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_META_DATA` (X'80')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_PARAMETER_META_DATA` (X'100')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DIAGNOSTICS` (X'200')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SQLJ` (X'400')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_XA_CALLS (IBM Data Server Driver for JDBC and SQLJ type 2 connectivity for Db2 on Linux, UNIX, and Windows systems only)` (X'800')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_META_CALLS` (X'2000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DATASOURCE_CALLS` (X'4000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_LARGE_OBJECT_CALLS` (X'8000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_T2ZOS` (X'10000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSTEM_MONITOR` (X'20000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_TRACEPOINTS` (X'40000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSPLEX` (X'80000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL` (X'FFFFFFFF')

To specify more than one trace, use one of these techniques:

- Use bitwise OR (|) operators with two or more trace values. For example, to trace DRDA flows and connection calls, specify this value for traceLevel:

```
TRACE_DRDA_FLOWS|TRACE_CONNECTION_CALLS
```

- Use a bitwise complement (tilde (~)) operator with a trace value to specify all except a certain trace. For example, to trace everything except DRDA flows, specify this value for traceLevel:

```
~TRACE_DRDA_FLOWS
```

fileAppend
Specifies whether to append to or overwrite the file that is specified by the traceFile parameter. `true` means that the existing file is not overwritten.

unsetLogWriter
Format:

```
public abstract void unsetLogWriter()
  throws java.sql.SQLException
```

Disables the global log writer override for future connections.

suspendTrace
Format:

```
public void suspendTrace()
  throws java.sql.SQLException
```

Suspends all global, `Connection`-level, or `DataSource`-level traces for current and future connections. `suspendTrace` can be called when the global log writer is enabled or disabled.

resumeTrace
Format:

```
public void resumeTrace()
  throws java.sql.SQLException
```

Resumes all global, `Connection`-level, or `DataSource`-level traces for current and future connections. `resumeTrace` can be called when the global log writer is enabled or disabled. If the global log writer is disabled, `resumeTrace` resumes `Connection`-level or `DataSource`-level traces. If the global log writer is enabled, `resumeTrace` resumes the global trace.

getLogWriter
Format:

```
public abstract java.io.PrintWriter getLogWriter()
  throws java.sql.SQLException
```

Returns the `PrintWriter` for the global log writer, if it is set. Otherwise, `getLogWriter` returns null.

getTraceFile
Format:

```
public abstract String getTraceFile()
  throws java.sql.SQLException
```

Returns the name of the destination file for the global log writer, if it is set. Otherwise, `getTraceFile` returns null.

getTraceDirectory
Format:

```
public abstract String getTraceDirectory()
  throws java.sql.SQLException
```

Returns the name of the destination directory for global log writer files, if it is set. Otherwise, `getTraceDirectory` returns null.

getTraceLevel
Format:

```
public abstract int getTraceLevel()
  throws java.sql.SQLException
```

Returns the trace level for the global trace, if it is set. Otherwise, `getTraceLevel` returns -1 (`TRACE_ALL`).

getTraceFileAppend

Format:

```
public abstract boolean getTraceFileAppend()
  throws java.sql.SQLException
```

Returns `true` if the global trace records are appended to the trace file. Otherwise, `getTraceFileAppend` returns `false`.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223

IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

DB2TraceManagerMXBean interface

The `com.ibm.db2.jcc.mx.DB2TraceManagerMXBean` interface is the means by which an application makes `DB2TraceManager` available as an MXBean for the remote trace controller.

DB2TraceManagerMXBean methods

setTraceFile

Format:

```
public void setTraceFile(String traceFile,
  boolean fileAppend, int traceLevel)
  throws java.sql.SQLException
```

Specifies the name of the file into which the remote trace manager writes trace information, and the type of information that is to be traced.

Parameter descriptions:

traceFileName

Specifies the file into which global trace information is written. This setting overrides the settings of the traceFile and logWriter properties for a `DataSource` or `DriverManager` connection.

When the form of `setLogWriter` with the traceFileName parameter is used, only one log file is written.

traceFileName can include a directory path.

fileAppend

Specifies whether to append to or overwrite the file that is specified by the traceFile parameter. `true` means that the existing file is not overwritten.

traceLevel

Specifies what to trace.

You can specify one or more of the following traces with the traceLevel parameter:

- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_NONE` (X'00')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTION_CALLS` (X'01')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_STATEMENT_CALLS` (X'02')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_CALLS` (X'04')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRIVER_CONFIGURATION` (X'10')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTS` (X'20')

- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS (X'40')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_META_DATA (X'80')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_PARAMETER_META_DATA (X'100')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DIAGNOSTICS (X'200')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SQLJ (X'400')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_META_CALLS (X'2000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DATASOURCE_CALLS (X'4000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_LARGE_OBJECT_CALLS (X'8000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_T2ZOS (X'10000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSTEM_MONITOR (X'20000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_TRACEPOINTS (X'40000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSPLEX (X'80000')
- com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL (X'FFFFFFFF')

To specify more than one trace, use one of these techniques:

- Use bitwise OR (|) operators with two or more trace values. For example, to trace DRDA flows and connection calls, specify this value for traceLevel:

```
TRACE_DRDA_FLOWS|TRACE_CONNECTION_CALLS
```

- Use a bitwise complement (tilde (~)) operator with a trace value to specify all except a certain trace. For example, to trace everything except DRDA flows, specify this value for traceLevel:

```
 ~TRACE_DRDA_FLOWS
```

getTraceFile

Format:

```
public void getTraceFile()
  throws java.sql.SQLException
```

Returns the name of the destination file for the remote trace controller, if it is set. Otherwise, `getTraceFile` returns null.

setTraceDirectory

Format:

```
public void setTraceDirectory(String traceDirectory,
  String baseTraceFileName,
  int traceLevel) throws java.sql.SQLException
```

Specifies the name of the directory into which the remote trace controller writes trace information, and the type of information that is to be traced.

Parameter descriptions:

traceDirectory

Specifies a directory into which trace information is written. This setting overrides the settings of the traceDirectory and logWriter properties for a `DataSource` or `DriverManager` connection.

Each JDBC driver connection is traced to a different file in the specified directory. The naming convention for the files in that directory depends on whether a non-null value is specified for baseTraceFileName:

- If a null value is specified for baseTraceFileName, a connection is traced to a file named traceFile_global_*n*.

  n is the *n*th JDBC driver connection.

- If a non-null value is specified for baseTraceFileName, a connection is traced to a file named *baseTraceFileName*_global_*n*.

  baseTraceFileName is the value of the baseTraceFileName parameter.

  n is the *n*th JDBC driver connection.

baseTraceFileName
Specifies the stem for the names of the files into which global trace information is written. The combination of baseTraceFileName and traceDirectory determines the full path name for the global trace log files.

traceLevel
Specifies what to trace.

You can specify one or more of the following traces with the traceLevel parameter:

- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_NONE` (X'00')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTION_CALLS` (X'01')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_STATEMENT_CALLS` (X'02')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_CALLS` (X'04')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRIVER_CONFIGURATION` (X'10')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTS` (X'20')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS` (X'40')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_RESULT_SET_META_DATA` (X'80')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_PARAMETER_META_DATA` (X'100')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DIAGNOSTICS` (X'200')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SQLJ` (X'400')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_META_CALLS` (X'2000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DATASOURCE_CALLS` (X'4000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_LARGE_OBJECT_CALLS` (X'8000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_T2ZOS` (X'10000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSTEM_MONITOR` (X'20000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_TRACEPOINTS` (X'40000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSPLEX` (X'80000')
- `com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL` (X'FFFFFFFF')

To specify more than one trace, use one of these techniques:

- Use bitwise OR (|) operators with two or more trace values. For example, to trace DRDA flows and connection calls, specify this value for traceLevel:

  ```
  TRACE_DRDA_FLOWS|TRACE_CONNECTION_CALLS
  ```

- Use a bitwise complement (tilde (~)) operator with a trace value to specify all except a certain trace. For example, to trace everything except DRDA flows, specify this value for traceLevel:

  ```
  ~TRACE_DRDA_FLOWS
  ```

getTraceFileAppend
Format:

```
public abstract boolean getTraceFileAppend()
  throws java.sql.SQLException
```

Returns `true` if trace records that are generated by the trace controller are appended to the trace file. Otherwise, `getTraceFileAppend` returns `false`.

getTraceDirectory
Format:

```
public void getTraceDirectory()
  throws java.sql.SQLException
```

Returns the name of the destination directory for trace records that are generated by the trace controller, if it is set. Otherwise, `getTraceDirectory` returns null.

getTraceLevel
Format:

```
public void getTraceLevel()
  throws java.sql.SQLException
```

Returns the trace level for the trace records that are generated by the trace controller, if it is set. Otherwise, `getTraceLevel` returns -1 (`TRACE_ALL`).

unsetLogWriter
Format:

```
public abstract void unsetLogWriter()
  throws java.sql.SQLException
```

Disables the global log writer override for future connections.

suspendTrace
Format:

```
public void suspendTrace()
  throws java.sql.SQLException
```

Suspends all global, `Connection`-level, or `DataSource`-level traces for current and future connections. `suspendTrace` can be called when the global log writer is enabled or disabled.

resumeTrace
Format:

```
public void resumeTrace()
  throws java.sql.SQLException
```

Resumes all global, `Connection`-level, or `DataSource`-level traces for current and future connections. `resumeTrace` can be called when the global log writer is enabled or disabled. If the global log writer is disabled, `resumeTrace` resumes `Connection`-level or `DataSource`-level traces. If the global log writer is enabled, `resumeTrace` resumes the global trace.

DB2Types class

The `com.ibm.db2.jcc.DB2Types` class provides fields that define IBM Data Server Driver for JDBC and SQLJ-only data types.

DB2Types fields

The following constants define types codes only for the IBM Data Server Driver for JDBC and SQLJ.

- public final static int BLOB_FILE = -100002
- public final static int CLOB_FILE = -100003
- public final static int CURSOR = -100008
- public final static int DECFLOAT = -100001
- public final static int XML_AS_BLOB_FILE = -100004
- public final static int XML_AS_CLOB_FILE = -100005
- public final static int TIMESTAMPTZ =-100010

DB2Version class

The `com.ibm.db2.jcc.DB2Version` class provides methods that return information about theIBM Data Server Driver for JDBC and SQLJ version.

DB2Version methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getBuildNumber
Format:

```
public static String getBuildNumber()
```

Returns the last portion of the driver version. For driver version *xx.yy.zzz*, the build number is *zzz*.

getCompatibleJREVersions
Format:

```
public static String[] getCompatibleJREVersions()
```

Returns the Java Runtime Environment versions that are compatible with the driver version.

getDriverName
Format:

```
public static String getDriverName()
```

Returns the name of the driver.

getDB2ConnectLicenseVersion
Format:

```
public static String getDB2ConnectLicenseVersion()
```

Returns the Db2 Connect version for which the IBM Data Server Driver for JDBC and SQLJ client license is valid.

This method is supported only for connections to Db2 for z/OS or Db2 for IBM i data servers.

getExpirationDateForDriver
Format:

```
public static java.util.Date getExpirationDateForDriver()
```

Returns the date on which the client license file for connections to Db2 for z/OS or Db2 for IBM i data servers expires.

This method is supported only for connections to Db2 for z/OS or Db2 for IBM i data servers.

getExpirationDateForDriverWithLicenseType
Format:

```
public static String getExpirationDateForDriverWithLicenseType()
```

Returns a String value that contains:

- The date on which the client license file for connections to Db2 for z/OS or Db2 for IBM i data servers expires.
- The type of license: temporary or permanent

This method is supported only for connections to Db2 for z/OS or Db2 for IBM i data servers.

getMajorVersion
Format:

```
public static String getMajorVersion()
```

Returns the first portion of the driver version. For driver version *xx*.*yy*.*zzz*, the major version is *xx*.

getMinorVersion
Format:

```
public static String getMinorVersion()
```

Returns the middle portion of the driver version. For driver version *xx*.*yy*.*zzz*, the minor version is *yy*.

getVersion
Format:

```
public static String getVersion()
```

Returns the driver version.

DB2XADataSource class

DB2XADataSource is a factory for XADataSource objects. An object that implements this interface is registered with a naming service that is based on the Java Naming and Directory Interface (JNDI).

The com.ibm.db2.jcc.DB2XADataSource class extends the com.ibm.db2.jcc.DB2BaseDataSource class, and implements the javax.sql.XADataSource, java.io.Serializable, and javax.naming.Referenceable interfaces.

DB2XADataSource methods

getDB2TrustedXAConnection
Formats:

```
public Object[] getDB2TrustedXAConnection(String user,
  String password,
  java.util.Properties properties)
  throws java.sql.SQLException
public Object[] getDB2TrustedXAConnection(
  java.util.Properties properties)
  throws java.sql.SQLException
public Object[] getDB2TrustedXAConnection(
  org.ietf.jgss.GSSCredential gssCredential,
  java.util.Properties properties)
  throws java.sql.SQLException
```

An application server using a system authorization ID uses this method to establish a trusted connection.

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

The following elements are returned in Object[]:

- The first element is a DB2TrustedXAConnection instance.
- The second element is a unique cookie for the generated XA connection instance.

If the first form of getDB2TrustedXAConnection provides a user ID and password, the second form of getDB2TrustedXAConnection uses the user ID and password of the DB2XADataSource object. The third form of getDB2TrustedXAConnection is for connections that use Kerberos security.

Parameter descriptions:

user
The authorization ID that is used to establish the trusted connection. For a connection that uses token authentication, the *user* value must be null.

password
The password for the authorization ID that is used to establish the trusted connection. For a connection that uses token authentication, the *password* value must be null.

gssCredential
If the data source uses Kerberos security, specifies a delegated credential that is passed from another principal.

properties
Properties for the connection. For a connection that uses token authentication, the accessToken and accessTokenType property values can be provided through the *properties* parameter.

getDB2TrustedPooledConnection
Format:

```
public Object[] getDB2TrustedPooledConnection(java.util.Properties properties)
  throws java.sql.SQLException
```

An application server using a system authorization ID uses this method to establish a trusted connection, using the user ID and password for the `DB2XADataSource` object.

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

The following elements are returned in Object[]:

- The first element is a trusted `DB2TrustedPooledConnection` instance.
- The second element is a unique cookie for the generated pooled connection instance.

Parameter descriptions:

properties
Properties for the connection.

getDB2XAConnection
Formats:

```
public DB2XAConnection getDB2XAConnection(String user,
  String password,
  java.util.Properties properties)
  throws java.sql.SQLException
public DB2XAConnection getDB2XAConnection(
   org.ietf.jgss.GSSCredential gssCredential,
  java.util.Properties properties)
  throws java.sql.SQLException
```

Establishes the initial untrusted connection in a heterogeneous pooling environment.

The second form of `getDB2XAConnection` is for connections that use Kerberos security.

Parameter descriptions:

user
The authorization ID that is used to establish the connection. For a connection that uses token authentication, the *user* value must be null.

password
The password for the authorization ID that is used to establish the connection. For a connection that uses token authentication, the *password* value must be null.

gssCredential
If the data source uses Kerberos security, specifies a delegated credential that is passed from another principal.

properties
Properties for the connection. For a connection that uses token authentication, the accessToken and accessTokenType property values can be provided through the *properties* parameter.

Related concepts

"Example of a distributed transaction that uses JTA methods" on page 623
Distributed transactions typically involve multiple connections to the same data source or different data sources, which can include data sources from different manufacturers.

Related tasks

"Creating and deploying DataSource objects" on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

DB2Xml interface

The `com.ibm.db2.jcc.DB2Xml` interface is used for declaring Java objects for use with the data server's XML data type.

DB2Xml methods

The following method is defined only for the IBM Data Server Driver for JDBC and SQLJ.

closeDB2Xml
Format:

```
public void closeDB2Xml()
  throws SQLException
```

Releases the resources that are associated with a com.ibm.jcc.DB2Xml object.

getDB2AsciiStream
Format:

```
public java.io.InputStream getDB2AsciiStream()
  throws SQLException
```

Retrieves data from a DB2Xml object, and converts the data to US-ASCII encoding.

getDB2BinaryStream
Format:

```
public java.io.InputStream getDB2BinaryStream()
  throws SQLException
```

Retrieves data from a `DB2Xml` object as a binary stream. The character encoding of the bytes in the binary stream is defined in the XML 1.0 specification.

getDB2Bytes
Format:

```
public byte[] getDB2Bytes()
  throws SQLException
```

Retrieves data from a `DB2Xml` object as a byte array. The character encoding of the bytes is defined in the XML 1.0 specification.

getDB2CharacterStream
Format:

```
public java.io.Reader getDB2CharacterStream()
  throws SQLException
```

Retrieves data from a DB2Xml object as a `java.io.Reader` object.

getDB2String
Format:

```
public String getDB2String()
  throws SQLException
```

Retrieves data from a DB2Xml object as a `String` value.

getDB2XmlAsciiStream
Format:

```
public InputStream getDB2XmlAsciiStream()
  throws SQLException
```

Retrieves data from a DB2Xml object, converts the data to US-ASCII encoding, and imbeds an XML declaration with an encoding specification for US-ASCII in the returned data.

getDB2XmlBinaryStream
Format:

```
public java.io.InputStream getDB2XmlBinaryStream(String targetEncoding)
  throws SQLException
```

Retrieves data from a DB2Xml object as a binary stream, converts the data to *targetEncoding*, and imbeds an XML declaration with an encoding specification for *targetEncoding* in the returned data.

Parameter:

targetEncoding
A valid encoding name that is listed in the IANA Charset Registry. The encoding names that are supported by the data server are listed in "Mappings of CCSIDs to encoding names for serialized XML output data".

getDB2XmlBytes
Format:

```
public byte[] getDB2XmlBytes(String targetEncoding)
  throws SQLException
```

Retrieves data from a DB2Xml object as a byte array, converts the data to *targetEncoding*, and imbeds an XML declaration with an encoding specification for *targetEncoding* in the returned data.

Parameter:

targetEncoding
A valid encoding name that is listed in the IANA Charset Registry. The encoding names that are supported by the data server are listed in "Mappings of CCSIDs to encoding names for serialized XML output data".

getDB2XmlCharacterStream
Format:

```
public java.io.Reader getDB2XmlCharacterStream()
  throws SQLException
```

Retrieves data from a DB2Xml object as a `java.io.Reader` object, converts the data to ISO-10646-UCS-2 encoding, and imbeds an XML declaration with an encoding specification for ISO-10646-UCS-2 in the returned data.

getDB2XmlString

Format:

```
public String getDB2XmlString()
  throws SQLException
```

Retrieves data from a DB2Xml object as a `String` object, converts the data to ISO-10646-UCS-2 encoding, and imbeds an XML declaration with an encoding specification for ISO-10646-UCS-2 in the returned data.

isDB2XmlClosed

Format:

```
public boolean isDB2XmlClosed()
  throws SQLException
```

Indicates whether a com.ibm.jcc.DB2Xml object has been closed.

Related concepts

"XML data retrieval in SQLJ applications" on page 165
When you retrieve data from XML columns of a database table in an SQLJ application, the output data must be explicitly or implicitly serialized.

"XML column updates in SQLJ applications" on page 164
In an SQLJ application, you can update or insert data into XML columns of a table at a Db2 data server using XML textual data. You can update or insert data into XML columns of a table using binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports binary XML data.

"XML data retrieval in JDBC applications" on page 93
In JDBC applications, you use `ResultSet.getXXX` or `ResultSet.getObject` methods to retrieve data from XML columns.

"XML column updates in JDBC applications" on page 91
In a JDBC application, you can update or insert data into XML columns of a table at a Db2 data server using XML textual data. You can update or insert data into XML columns of a table using binary XML data (data that is in the Extensible Dynamic Binary XML Db2 Client/Server Binary XML Format), if the data server supports binary XML data.

DB2XmlAsBlobFileReference class

The `com.ibm.db2.jcc.DB2XmlAsBlobFileReference` class is subclass of `DB2FileReference` that is used for creating XML AS BLOB file reference variable objects. This class applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS Version 9 or later.

DB2XmlAsBlobFileReference constructor

The following constructor is defined only for the IBM Data Server Driver for JDBC and SQLJ.

DB2XmlAsBlobFileReference

Format:

```
public DB2XmlAsBlobFileReference(String fileName)
  throws java.sql.SQLException
```

Constructs a `DB2XmlAsBlobFileReference` object for an XML AS BLOB file reference variable.

Parameter descriptions:

fileName

The name of the file for the file reference variable. The name must specify the absolute path name for an existing HFS file.

DB2XmlAsClobFileReference class

The com.ibm.db2.jcc.DB2XmlAsClobFileReference class is subclass of DB2FileReference that is used for creating XML AS CLOB file reference variable objects. This class applies only to IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to Db2 for z/OS Version 9 or later.

DB2XmlAsClobFileReference constructor

The following constructor is defined only for the IBM Data Server Driver for JDBC and SQLJ.

DB2XmlAsClobFileReference

Format:

```
public DB2XmlAsClobFileReference(String fileName,
                                 int fileCcsid)
  throws java.sql.SQLException
public DB2XmlAsClobFileReference(String fileName,
                                 String fileEncoding)
  throws java.sql.SQLException
```

Constructs a DB2XmlAsClobFileReference object for an XML AS CLOB file reference variable.

Parameter descriptions:

fileName
The name of the file for the file reference variable. The name must specify the absolute path name for an existing HFS file.

fileCcsid
The CCSID of the data in the file for the file reference variable.

fileEncoding
The encoding scheme of the data in the file for the file reference variable.

DBTimestamp class

The com.ibm.db2.jcc.DBTimestamp class can be used to create timestamp objects with a precision of up to picoseconds and time zone information. This class is primarily for support of the SQL TIMESTAMP WITH TIME ZONE data type, which is supported only by Db2 for z/OS.

The com.ibm.db2.jcc.DBTimestamp class is a subclass of the java.sql.Timestamp class. Therefore, a com.ibm.db2.jcc.DBTimestamp object can be used with any methods that normally operate on a java.sql.Timestamp object, or take a java.sql.Timestamp object as an argument.

The IBM Data Server Driver for JDBC and SQLJ returns a DBTimestamp object for all JDBC methods that return timestamp information, such as ResultSet.getTimestamp or CallableStatement.getTimestamp.

DBTimestamp constructor

The following constructor is defined only for the IBM Data Server Driver for JDBC and SQLJ.

DBTimestamp

Formats:

```
public DBTimestamp(long time,
  java.util.Calendar calendar)
  throws java.sql.SQLException
public DBTimestamp(long time)
  throws java.sql.SQLException
public DBTimestamp(java.sql.Timestamp timestamp)
  throws java.sql.SQLException
public DBTimestamp(java.sql.Timestamp timestamp,
  java.util.Calendar calendar)
  throws java.sql.SQLException
```

Constructs a DBTimestamp object.

Parameter descriptions:

time
The number of milliseconds since January 1, 1970.

timestamp
A `Timestamp` value with a precision of up to picoseconds.

calendar
The `Calendar` value that provides the time zone.

DBTimestamp methods

getPicos
Formats:

```
public long getPicos()
```

Returns the fractional seconds component of a `DBTimestamp` value.

getTimeZone
Formats:

```
public java.util.TimeZone getTimeZone()
```

Returns the time zone component of a `DBTimestamp` value.

setPicos
Format:

```
public void setPicos(long p)
  throws SQLException
```

Assigns the given value to the fractional seconds component of a `DBTimestamp` value.

Parameter descriptions:

p
A value between 0 and 999999999999, inclusive, which is the fractional sections component of a `DBTimestamp` value.

setTimeZone
Format:

```
public void setTimeZone(java.util.TimeZone timeZone)
  throws SQLException
```

Assigns the given value to the time zone component of a `DBTimestamp` value.

Parameter descriptions:

timeZone
The time zone component of a `DBTimestamp` value.

valueOfDBString
Format:

```
public static DBTimestamp valueOfDBString(String s)
  throws java.lang.IllegalArgumentException
```

Constructs a `DBTimestamp` value from the string representation of a timestamp value.

Parameter descriptions:

s
The string representation of a timestamp value. The value must be in one of the following formats:

```
yyyy-mm-dd.hh.mm.ss[.fffffffffffff]-th:tm
yyyy-mm-dd hh:mm:ss[.fffffffffffff]-th:tm
yyyy-mm-dd.hh.mm.ss[.fffffffffffff]
yyyy-mm-dd hh:mm:ss[.fffffffffffff]
```

- *yyyy* is a year.
- *mm* is a month.
- *dd* is a day.
- *hh* is hours.
- *mm* is minutes.
- *ss* is seconds.
- *[.fffffffffffff]* is one to 12 optional fractions of seconds.
- *th* is the hours component of a time zone.
- *tm* is the minutes component of a time zone.

toDBString
Format:

```
public String toDBString(boolean includeTimeZone)
```

Returns the string representation of a DBTimestamp object.

The returned value has one of the following formats:

```
yyyy-mm-dd.hh.mm.ss[.fffffffffffff]-th:tm
yyyy-mm-dd.hh.mm.ss[.fffffffffffff]
```

Parameter description:

includeTimeZone
Specifies whether to include the time zone (*-th*:*tm*) in the returned string.

LoadResult class

The com.ibm.db2.jcc.LoadResult class provides methods for returning the results of a DB2Connection.zLoad invocation.

LoadResult methods

The following methods are defined only for the IBM Data Server Driver for JDBC and SQLJ.

getMessage
Format:

```
public String getMessage()
```

Returns error message text from the load operation.

getReturnCode
Format:

```
public int getReturnCode()
```

Returns the return code from the load operation.

JDBC differences between versions of the IBM Data Server Driver for JDBC and SQLJ

Before you can upgrade your JDBC applications from older to newer versions of the IBM Data Server Driver for JDBC and SQLJ, you need to understand the differences between those drivers.

Supported methods

For a list of methods that the IBM Data Server Driver for JDBC and SQLJ supports, see the information on driver support for JDBC APIs.

Use of progressive streaming by the JDBC drivers

For IBM Data Server Driver for JDBC and SQLJ, Version 3.50 or later, progressive streaming, which is also known as dynamic data format, behavior is the default for LOB retrieval, for connections to Db2 on Linux, UNIX, and Windows systems Version 9.5 or later.

Progressive streaming is supported in the IBM Data Server Driver for JDBC and SQLJ Version 3.1 or later, but for IBM Data Server Driver for JDBC and SQLJ version 3.2 or later, progressive streaming behavior is the default for LOB and XML retrieval, for connections to Db2 for z/OS Version 9.1 or later.

Previous versions of the IBM Data Server Driver for JDBC and SQLJ did not support progressive streaming.

Important: With progressive streaming, when you retrieve a LOB or XML value from a `ResultSet` into an application variable, you can manipulate the contents of that application variable until you move the cursor or close the cursor on the `ResultSet`. After that, the contents of the application variable are no longer available to you. If you perform any actions on the LOB in the application variable, you receive an `SQLException`. For example, suppose that progressive streaming is enabled, and you execute statements like this:

```
…
ResultSet rs = stmt.executeQuery("SELECT CLOBCOL FROM MY_TABLE");
rs.next();                // Retrieve the first row of the ResultSet
Clob clobFromRow1  = rs.getClob(1);
                          // Put the CLOB from the first column of
                          // the first row in an application variable
String substr1Clob = clobFromRow1.getSubString(1,50);
                          // Retrieve the first 50 bytes of the CLOB
rs.next();                // Move the cursor to the next row.
                          // clobFromRow1 is no longer available.
// String substr2Clob = clobFromRow1.getSubString(51,100);
                          // This statement would yield an SQLException
Clob clobFromRow2  = rs.getClob(1);
                          // Put the CLOB from the first column of
                          // the second row in an application variable
rs.close();               // Close the ResultSet.
                          // clobFromRow2 is also no longer available.
```

After you execute `rs.next()` to position the cursor at the second row of the `ResultSet`, the CLOB value in clobFromRow1 is no longer available to you. Similarly, after you execute `rs.close()` to close the `ResultSet`, the values in clobFromRow1 and clobFromRow2 are no longer available.

To avoid errors that are due to this changed behavior, you need to take one of the following actions:

- Modify your applications.

  Applications that retrieve LOB data into application variables can manipulate the data in those application variables only until the cursors that were used to retrieve the data are moved or closed.
- Disable progressive streaming by setting the `progressiveStreaming` property to `DB2BaseDataSource.NO` (2).

ResultSetMetaData values for IBM Data Server Driver for JDBC and SQLJ

For the IBM Data Server Driver for JDBC and SQLJ version 4.0 or later, the default behavior of `ResultSetMetaData.getColumnName` and `ResultSetMetaData.getColumnLabel` differs from the default behavior for earlier JDBC drivers.

If you need to use IBM Data Server Driver for JDBC and SQLJ version 4.0 or later, but your applications need to return the `ResultSetMetaData.getColumnName` and `ResultSetMetaData.getColumnLabel` values that were returned with older JDBC drivers, you can set the useJDBC4ColumnNameAndLabelSemantics `Connection` and `DataSource` property to `DB2BaseDataSource.NO` (2).

Batch updates with automatically generated keys have different results in different driver versions

With the IBM Data Server Driver for JDBC and SQLJ version 3.52 or later, preparing an SQL statement for retrieval of automatically generated keys is supported.

With the IBM Data Server Driver for JDBC and SQLJ version 3.50 or version 3.51, preparing an SQL statement for retrieval of automatically generated keys and using the `PreparedStatement` object for batch updates causes an `SQLException`.

Versions of the IBM Data Server Driver for JDBC and SQLJ before Version 3.50 do not throw an `SQLException` when an application calls the `addBatch` or `executeBatch` method on a `PreparedStatement` object that is prepared to return automatically generated keys. However, the `PreparedStatement` object does not return automatically generated keys.

Batch updates of data on Db2 for z/OS servers have different results in different driver versions

After you successfully invoke an `executeBatch` statement, the IBM Data Server Driver for JDBC and SQLJ returns an array. The purpose of the array is to indicate the number of rows that are affected by each SQL statement that is executed in the batch.

If the following conditions are true, the IBM Data Server Driver for JDBC and SQLJ returns `Statement.SUCCESS_NO_INFO` (-2) in the array elements:

- The application is connected to a subsystem that is in Db2 for z/OS Version 8 new-function mode, or later.
- The application is using Version 3.1 or later of the IBM Data Server Driver for JDBC and SQLJ.
- The IBM Data Server Driver for JDBC and SQLJ uses multi-row INSERT operations to execute batch updates.

This occurs because with multi-row INSERT, the database server executes the entire batch as a single operation, so it does not return results for individual SQL statements.

If you are using an earlier version of the IBM Data Server Driver for JDBC and SQLJ, or you are connected to a data source other than Db2 for z/OS Version 8 or later, the array elements contain the number of rows that are affected by each SQL statement.

Batch updates and deletes of data on Db2 for z/OS servers have different size limitations in different driver versions

Before IBM Data Server Driver for JDBC and SQLJ version 3.59 or 4.9, a `DisconnectException` with error code -4499 was thrown for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS if the size of an update or delete batch was greater than 32KB. Starting with version 3.59 or 4.9, this restriction no longer exists, and the exception is no longer thrown.

Initial value of the CURRENT CLIENT_ACCTNG special register

For a JDBC or SQLJ application that runs under the IBM Data Server Driver for JDBC and SQLJ version 2.6 or later, using type 4 connectivity, the initial value for the Db2 for z/OS CURRENT CLIENT_ACCTNG special register is the concatenation of the Db2 for z/OS version and the value of the clientWorkStation property. For any other JDBC driver, version, and connectivity, the initial value is not set.

Properties that control the use of multi-row FETCH

Before version 3.7 and version 3.51 of the IBM Data Server Driver for JDBC and SQLJ, multi-row FETCH support was enabled and disabled through the useRowsetCursor property, and was available only for scrollable cursors, and for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS. Starting with version 3.7 and 3.51:

- For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, the IBM Data Server Driver for JDBC and SQLJ uses only the enableRowsetSupport property to determine whether to use multi-row FETCH for scrollable or forward-only cursors.
- For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to z/OS or Db2 on Linux, UNIX, and Windows systems, or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 on Linux, UNIX, and Windows systems, the driver uses the enableRowsetSupport property to determine whether to use multi-row FETCH for scrollable cursors, if enableRowsetSupport is set. If enableRowsetSupport is not set, the driver uses the useRowsetCursor property to determine whether to use multi-row FETCH.

JDBC 1 positioned updates and deletes and multi-row FETCH

Before version 3.7 and version 3.51 of the IBM Data Server Driver for JDBC and SQLJ, multi-row FETCH from Db2 for z/OS tables was controlled by the useRowsetCursor property. If an application contained JDBC 1 positioned update or delete operations, and multi-row FETCH support was enabled, the IBM Data Server Driver for JDBC and SQLJ permitted the update or delete operations, but unexpected updates or deletes might occur.

Starting with version 3.7 and 3.51 of the IBM Data Server Driver for JDBC and SQLJ, the enableRowsetSupport property enables or disables multi-row FETCH from Db2 for z/OS tables or Db2 on Linux, UNIX, and Windows systems tables. The enableRowsetSupport property overrides the useRowsetCursor property. If multi-row FETCH is enabled through the enableRowsetSupport property, and an application contains a JDBC 1 positioned update or delete operation, the IBM Data Server Driver for JDBC and SQLJ throws an `SQLException`.

Valid forms of prepareStatement for retrieval of automatically generated keys from a Db2 for z/OS view

Starting with version 3.57 or version 4.7 of the IBM Data Server Driver for JDBC and SQLJ, if you are inserting data into a view on a Db2 for z/OS data server, and you want to retrieve automatically generated keys, you need to use one of the following methods to prepare the SQL statement that inserts rows into the view:

```
Connection.prepareStatement(sql-statement, String [] columnNames);
Connection.prepareStatement(sql-statement, int [] columnIndexes);
Statement.executeUpdate(sql-statement, String [] columnNames);
Statement.executeUpdate(sql-statement, int [] columnIndexes);
```

Data loss for TIMESTAMP(p) column updates using setString

If you use a `setString` call to pass an input value to a TIMESTAMP(*p*) column, it is possible to send a value with a precision of greater than nine to the column.

Before version 3.59 or version 4.9 of the IBM Data Server Driver for JDBC and SQLJ, data loss could occur if the sendDataAsIs property was set to `false`, and the precision of the input value was greater than nine.

Starting with version 3.59 and version 4.9 of the IBM Data Server Driver for JDBC and SQLJ, data loss does not occur if the TIMESTAMP(*p*) column is large enough to accommodate the input value.

Special processing for `java.sql.Timestamp` input data

Before version 3.63 or 4.13 of the IBM Data Server Driver for JDBC and SQLJ, if the target data type is not known, the target data server supports TIMESTAMP WITH TIME ZONE, and the input data type is `java.sql.Timestamp`, the driver chooses TIMESTAMP WITH TIME ZONE as the target type. Starting with version 3.63 or 4.13, if the target data type is not known, the target data server supports TIMESTAMP WITH TIME ZONE, and the input data type is `java.sql.Timestamp`, the driver chooses TIMESTAMP WITH TIME ZONE as the target type, except when the input object has a value of 0001-01-01-00:00:00.000000 or 9999-12-31-23:59:59.999999. In those cases, the driver chooses the TIMESTAMP type, without a time zone. Use of the TIMESTAMP data type in those two cases prevents an overflow condition from occurring because of adjustment of the value for the implied time zone. The implied time zone is the time zone of the Java virtual machine (JVM). Starting with version 3.65 or 4.15, the timestamps for which the driver chooses the TIMESTAMP type, without the time zone, are 0001-01-01, with any time, or 9999-12-31, with any time.

Change to result set column name for getColumns

In version 4.12 or earlier of the IBM Data Server Driver for JDBC and SQLJ, the `DatabaseMetaData.getColumns` method returned a result set that contained a column named SCOPE_CATLOG. In version 4.13 or later of the IBM Data Server Driver for JDBC and SQLJ, the name of that column is SCOPE_CATALOG. If you want the IBM Data Server Driver for JDBC and SQLJ to continue to use the column name SCOPE_CATLOG, set `DataSource` or `Connection` property useJDBC41DefinitionForGetColumns to `DB2BaseDataSource.NO` (2).

Changes to defaults for global configuration properties db2.jcc.maxRefreshInterval, db2.jcc.maxTransportObjects, and db2.jcc.maxTransportObjectWaitTime

The default values for global configuration properties db2.jcc.maxRefreshInterval, db2.jcc.maxTransportObjects, and db2.jcc.maxTransportObjectWaitTime change in version 3.63 and 4.13 of the IBM Data Server Driver for JDBC and SQLJ. The following table lists the old and new defaults.

Configuration property	Default before versions 3.63 and 4.13	Default for versions 3.63 and 4.13 or later
db2.jcc.maxRefreshInterval	30 seconds	10 seconds
db2.jcc.maxTransportObjects	-1 (unlimited)	1000
db2.jcc.maxTransportObjectWaitTime	-1 (unlimited)	1 second

Changes to the default value for Connection and DataSource property timerLevelForQueryTimeOut

The default value for `Connection` and `DataSource` property timerLevelForQueryTimeOut changes in version 4.26 of the IBM Data Server Driver for JDBC and SQLJ. The following table lists the old and new defaults.

`Connection` and `DataSource` property	Default value before version 4.26	Default value for version 4.26 or later
timerLevelForQueryTimeOut	1 (QUERYTIMEOUT_STATEMENT_LEVEL)	2 (QUERYTIMEOUT_CONNECTION_LEVEL)

Changes to default values for Connection and DataSource property maxTransportObjects

The default value for `Connection` and `DataSource` properties maxTransportObjects changes in version 3.63 and 4.13 of the IBM Data Server Driver for JDBC and SQLJ. The following table lists the old and new defaults.

`Connection` and `DataSource` property	**Default value before versions 3.63 and 4.13**	**Default value for versions 3.63 and 4.13 or later**
maxTransportObjects	-1 (unlimited)	1000

maxRetriesForClientReroute, memberConnectTimeout, and retryIntervalForClientReroute no longer apply to connections to a Db2 for z/OS data sharing group (driver versions 3.72.52 and 4.25.13)

Starting with IBM Data Server Driver for JDBC and SQLJ versions 3.72.52 and 4.25.13, for connections to a Db2 for z/OS data sharing group. During automatic client reroute, the connection is retried once, using the IP address that is associated with the data sharing group.

Changes to default values for Connection and DataSource properties maxRetriesForClientReroute and retryIntervalForClientReroute for connections to a Db2 for z/OS data sharing group (driver version 3.64)

The default value for `Connection` and `DataSource` properties maxRetriesForClientReroute and retryIntervalForClientReroute change in version 3.64 , of the IBM Data Server Driver for JDBC and SQLJ for connections to a Db2 for z/OS data sharing group. The following table lists the new defaults.

`Connection` and `DataSource` property	**Default value before versions 3.64**	**Default value for versions 3.64 , or later**
maxRetriesForClientReroute	Retry for 10 minutes, with a wait time between retries that increases as the length of time from the first retry increases.	5
retryIntervalForClientReroute	Retry for 10 minutes, with a wait time between retries that increases as the length of time from the first retry increases.	0

Changes to the default value and meaning of a retry for Connection and DataSource property maxRetriesForClientReroute for connections to a Db2 for z/OS data sharing group

The default value for `Connection` and `DataSource` property maxRetriesForClientReroute and the meaning of a retry change in versions 3.66 and 4.16, and again in version 4.25 of the IBM Data Server Driver for JDBC and SQLJ for connections to a Db2 for z/OS data sharing group.

The following table shows the meaning of a retry for different IBM Data Server Driver for JDBC and SQLJ versions.

Table 100. Meaning of a retry for different driver versions

Driver version	**Retry behavior**
Before versions 3.66 and 4.16	A retry is one attempt to connect to one member of the data sharing group.

Table 100. Meaning of a retry for different driver versions (continued)

Driver version	Retry behavior
Versions 3.66 through 3.72, and versions 4.16 through 4.24	A retry is one attempt to connect to each member of the data sharing group other than the failed member, and then to the group IP address. This behavior change might make it necessary to lower the value of maxRetriesForClientReroute.
Version 4.25 or later	A retry is one attempt to connect to the group IP address of the data sharing group. If the enableSysplexWLB property is set to `true`, the default value of maxRetriesForClientReroute is 1.

The following table shows the maxRetriesForClientReroute default for different IBM Data Server Driver for JDBC and SQLJ versions.

Table 101. Default maxRetriesForClientReroute value for different driver versions

Driver version	Default value
Before versions 3.66 and 4.16	The default depends on whether the connection is a first connection or a retry: • For the first connection to a data sharing group, if maxRetriesForClientReroute and retryIntervalForClientReroute are not set, and the enableSysplexWLB property is set to `true`, the default is to retry five times with a retry interval of 0. • For a failover during a subsequent connection to a data sharing group, if maxRetriesForClientReroute and retryIntervalForClientReroute are not set, the enableSysplexWLB property is set to `true`, and a cached server list or an alternate server is specified, the default is to retry the connection for 10 minutes, with a wait time between retries that increases as the length of time from the first retry increases.
Versions 3.66 and 4.16, or later	If the enableSysplexWLB property is set to `true`, the default is 1.
Version 4.25 or later	One attempt to connect to the datasource IP of the data sharing group other than the failed member. The retries can be increased using the property maxRetriesForClientReroute. If the enableSysplexWLB property is set to `true`, the default is 1.

Change to the meaning of a retry for connections to a Db2 on Linux, UNIX, and Windows systems Db2 pureScale instance (driver versions 3.67 and 4.17)

The meaning of a retry for automatic client reroute changes in version 3.67 and 4.17 of the IBM Data Server Driver for JDBC and SQLJ for connections to a Db2 on Linux, UNIX, and Windows systems Db2 pureScale instance.

The following table shows the old and new meanings.

Meaning of a retry before versions 3.67 and 4.17	Meaning of a retry for versions 3.67 and 4.17, or later
One attempt to connect to one member of the Db2 pureScale instance.	One attempt to connect to all members of the Db2 pureScale instance. This change might make it necessary to lower the value of maxRetriesForClientReroute.

Changes to default values for client info properties for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS

The default values for client info properties for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS change in version 3.64 of the IBM Data Server Driver for JDBC and SQLJ. The following table lists the old and new defaults.

Client into property	Default value before versions 3.64	Default value for versions 3.64 or later
clientApplicationInformation	Empty string	The string "db2jcc_application"
clientAccountingInformation	Empty string	Empty string
clientWorkstation	Empty string	The string "RRSAF".
clientUser	Empty string	The user ID that was specified for the connection. If no user ID was specified, the RACF user ID is used.

Changes to maximum lengths for client info properties for Db2 for z/OS

The maximum lengths for client info properties for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS change in version 3.66 and 4.16 of the IBM Data Server Driver for JDBC and SQLJ. The following table lists the old and new lengths.

Client into property	Maximum length before versions 3.68 and 4.18	Maximum length for versions 3.68 and 4.18, or later
clientApplicationInformation	32	255
clientAccountingInformation	22	255
clientWorkstation	18	255
clientUser	16	128

Change to default for global configuration property db2.jcc.enableInetAddressGetHostName

Starting with versions 3.65 and 4.15 of the IBM Data Server Driver for JDBC and SQLJ, the default for db2.jcc.enableInetAddressGetHostName is `false`. For versions 3.64 or earlier, the default is `true`.

Changes to the behavior of the xmlFormat property

Starting with version 4.15 of the IBM Data Server Driver for JDBC and SQLJ, the xmlFormat `Connection` and `DataSource` property applies only to XML data retrieval, instead of to XML data update and retrieval. In addition, the default behavior has changed to retrieval of XML data in textual XML format, regardless of whether the data server supports binary XML format.

For update of data in XML columns, xmlFormat has no effect. If the input data is binary XML data, and the data server does not support binary XML data, the input data is converted to textual XML data. Otherwise, no conversion occurs.

Changes to the default value of Connection and DataSource property useCachedCursor

For connections to Db2 on Linux, UNIX, and Windows systems, the default value of the useCachedCursor `Connection` and `DataSource` property has changed.

The default is:

- `false`, if the driver is at one of the following levels:
  - Version 3.67 or 4.17, or later
  - Version 3.64
- `true`, for any other driver versions.

If the driver version is 3.67 or 4.17, or later, or 3.64 , and the deferPrepares property is set to true, the driver behaves as if useCachedCursor is set to false, regardless of the useCachedCursor setting.

Changes to driver behavior for failure of seamless failover during automatic client reroute

Before versions 3.67 and 4.17 of the IBM Data Server Driver for JDBC and SQLJ, seamless failover error behavior was that after 10 attempts to reconnect to a failover server and execute the SQL statement that failed previously, the driver issued an `SQLException` with SQL error code -20542.

Starting with versions 3.67 and 4.17 of the IBM Data Server Driver for JDBC and SQLJ, seamless failover error behavior is that after one attempt to reconnect to a failover server and execute the SQL statement that failed previously, the driver issues an `SQLException` with SQL error code -4228.

Change to trace polling default

The default for db2.jcc.tracePolling is false before Version 3.69 of the IBM Data Server Driver for JDBC and SQLJ, and the default is true for Version 3.69 or later.

Change to the default security mechanism

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default security mechanism is `CLEAR_TEXT_PASSWORD_SECURITY`. If the data server does not support `CLEAR_TEXT_PASSWORD_SECURITY`, but supports `ENCRYPTED_USER_AND_PASSWORD_SECURITY`, the driver changes the security mechanism to `ENCRYPTED_USER_AND_PASSWORD_SECURITY` and attempts to connect to the data server. Any other mismatch in security mechanism support between the requester and the data server results in an error.

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ:

- The default security mechanism is `ENCRYPTED_USER_AND_PASSWORD_SECURITY`. If the data server does not support `ENCRYPTED_USER_AND_PASSWORD_SECURITY`, but supports `CLEAR_TEXT_PASSWORD_SECURITY`, the driver changes the security mechanism to `CLEAR_TEXT_PASSWORD_SECURITY` and attempts to connect to the data server. The connection retry using `CLEAR_TEXT_PASSWORD_SECURITY` might cause a slight performance impact. Any other mismatch in security mechanism support between the requester and the data server results in an error.
- A connection to a Db2 for z/OS subsystem or data sharing group that uses the default security mechanism of `ENCRYPTED_USER_AND_PASSWORD_SECURITY` and AES encryption is successful only if the z/OS Integrated Cryptographic Service Facility (ICSF) is enabled on the z/OS system where each subsystem or data sharing member is installed. ICSF is required for decrypting the user ID and password. If ICSF is not installed, you need to set the security mechanism to `CLEAR_TEXT_PASSWORD_SECURITY`.

Change to the default encryption algorithm

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default encryption algorithm is 56-bit DES encryption (1).

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default encryption is 256-bit AES encryption (2).

Changes to driver behavior for a data type mismatch between a host variable and a column

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, when the SQLJ profile customizer (db2sqljcustomize) bound a host variable to a column, and there was a mismatch between the host variable data type and the column data type, db2sqljcustomize took no action.

Starting with Version 4.33 of the driver, when there is a data type mismatch, and db2sqljcustomize option -onTypeMismatch is not set, db2sqljcustomize issues a warning and continues the customization process.

Changes to driver behavior on truncation of input data

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, when a value was inserted into a column, and the value was too large for the column, the driver took no action.

Starting with Version 4.33 of the driver, when data that is too large for a column is inserted into the column, the default behavior is that the driver issues a warning. To cause the same behavior as in earlier versions of the driver, set `Connection` and `DataSource` property onDataTruncation to `DB2BaseDataSource.ON_DATA_TRUNCATION_NO_ACTION_VALUE` (3), or set configuration property db2.jcc.onDataTruncation or db2.jcc.override.onDataTruncation to 3.

Changes to the default values for maxRetriesForClientReroute and retryIntervalForClientReroute

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, when neither maxRetriesForClientReroute nor retryIntervalForClientReroute are explicitly set, the driver uses the following values:

- For a connection to a data server other than Db2 for z/OS, the connection is retried for 10 minutes.
- For a connection to a Db2 for z/OS data sharing group, if the initial connection is unsuccessful, the driver uses a maxRetriesForClientReroute value of 1 and a retryIntervalForClientReroute value of 0 for further retries.

IBM Netezza connection through the IBM Data Server Driver for JDBC and SQLJ

IBM Netezza® clients can use the IBM Data Server Driver for JDBC and SQLJ to connect to a database server. Minimal client-side configuration is needed when switching from an nzjdbc3 driver to the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ readily accepts Netezza configuration settings:

- The Class.forName method will accept the Netezza driver:

```
Class.forName("org.netezza.Driver");
```

- The JDBC Connection URL will accept the "netezza" subprotocol:

```
jdbc:netezza://host:port/databaseName
```

- You can use the `org.netezza.datasource.NzDataSource` class to construct a DataSource for acquiring connections to the server.

The IBM Data Server Driver for JDBC and SQLJ uses a default port number of 50,000 when connecting an IBM Netezza client.

Compatible properties

Certain Netezza driver properties can be used to establish connection settings with the IBM Data Server Driver for JDBC and SQLJ. The following Netezza driver properties will be recognized by the IBM Data Server Driver for JDBC and SQLJ. They can be used in place of corresponding IBM Data Server Driver for JDBC and SQLJ properties with similar functionality if specified in camel case, all lowercase, or all uppercase letters.

Table 102. The following table lists several common Netezza driver properties that can be used in Netezza client applications instead of similar IBM Data Server Driver for JDBC and SQLJ properties.

Netezza Driver Property	**IBM Data Server Driver for JDBC and SQLJ Property**
applicationName	clientProgramName
autocommit	autoCommit
batchSize	fetchSize
caCertFile	sslCertLocation
clientHostName	clientWorkstation
clientUser	clientUser
database	databaseName
description	description
host	serverName
logDirPath	traceDirectory
loginTimeout	loginTimeout
name	dataSourceName
password	password
port	portNumber
readonly	readOnly
schema	currentSchema
securityLevel	sslConnection

Security specifications

Set the Netezza securityLevel property to "preferredSecured" or "onlySecured" if you would like to enable SSL connections in the application. Any other value for securityLevel will disable SSL connections.

Incompatibilities

- The IBM Data Server Driver for JDBC and SQLJ will not throw an error if you use a Netezza driver property other than the aforementioned compatible properties.
- The IBM Data Server Driver for JDBC and SQLJ will use empty functions in the case of unsupported application programming interfaces.

- The Netezza logLevel property is not supported with the IBM Data Server Driver for JDBC and SQLJ. Implement a driver logging mechanism to evaluate IBM Data Server Driver for JDBC and SQLJ traceLevel settings to learn which trace settings best match your needs.

Examples of ResultSetMetaData.getColumnName and ResultSetMetaData.getColumnLabel values

For the IBM Data Server Driver for JDBC and SQLJ version 4.0 and later, the default behavior of `ResultSetMetaData.getColumnName` and `ResultSetMetaData.getColumnLabel` differs from the default behavior for earlier JDBC drivers. You can use the useJDBC4ColumnNameAndLabelSemantics property to change this behavior.

The following examples show the values that are returned for IBM Data Server Driver for JDBC and SQLJ Version 4.0, and for previous JDBC drivers, when the useJDBC4ColumnNameAndLabelSemantics property is not set.

All queries use a table that is defined like this:

```
CREATE TABLE MYTABLE(INTCOL INT)
```

Example: The following query contains an AS CLAUSE, which defines a label for a column in the result set:

```
SELECT MYCOL AS MYLABEL FROM MYTABLE
```

The following table lists the `ResultSetMetaData.getColumnName` and `ResultSetMetaData.getColumnName` values that are returned for the query:

Table 103. ResultSetMetaData.getColumnName and ResultSetMetaData.getColumnName before and after IBM Data Server Driver for JDBC and SQLJ Version 4.0 for a query with an AS CLAUSE

	Behavior before IBM Data Server Driver for JDBC and SQLJ Version 4.0		**Behavior for IBM Data Server Driver for JDBC and SQLJ Version 4.0 and later**	
Target data source	**getColumnName value**	**getColumnLabel value**	**getColumnName value**	**getColumnLabel value**
Db2 on Linux, UNIX, and Windows systems	MYLABEL	MYLABEL	MYCOL	MYLABEL
IBM Informix	MYLABEL	MYLABEL	MYCOL	MYLABEL
Db2 for z/OS Version 8 or later, and Db2 for IBM i V5R3 and later	MYLABEL	MYLABEL	MYCOL	MYLABEL
Db2 for z/OS Version 7, and Db2 for IBM i V5R2	MYLABEL	MYLABEL	MYLABEL	MYLABEL

Example: The following query contains no AS clause:

```
SELECT MYCOL FROM MYTABLE
```

The `ResultSetMetaData.getColumnName` and `ResultSetMetaData.getColumnLabel` methods on the query return MYCOL, regardless of the target data source.

Example: On a Db2 for z/OS or Db2 for IBM i data source, a LABEL ON statement is used to define a label for a column:

```
LABEL ON COLUMN MYTABLE.MYCOL IS 'LABELONCOL'
```

The following query contains an AS CLAUSE, which defines a label for a column in the `ResultSet`:

```
SELECT MYCOL AS MYLABEL FROM MYTABLE
```

The following table lists the `ResultSetMetaData.getColumnName` and `ResultSetMetaData.getColumnName` values that are returned for the query.

Table 104. ResultSetMetaData.getColumnName and ResultSetMetaData.getColumnName before and after IBM Data Server Driver for JDBC and SQLJ Version 4.0 for a table column with a LABEL ON statement in a query with an AS CLAUSE

	Behavior before IBM Data Server Driver for JDBC and SQLJ Version 4.0		**Behavior for IBM Data Server Driver for JDBC and SQLJ Version 4.0 and later**	
Target data source	**getColumnName value**	**getColumnLabel value**	**getColumnName value**	**getColumnLabel value**
Db2 for z/OS Version 8 or later, and Db2 for IBM i V5R3 and later	MYLABEL	LABELONCOL	MYCOL	MYLABEL
Db2 for z/OS Version 7, and Db2 for IBM i V5R2	MYLABEL	LABELONCOL	MYCOL	LABELONCOL

Example: On a Db2 for z/OS or Db2 for IBM i data source, a LABEL ON statement is used to define a label for a column:

```
LABEL ON COLUMN MYTABLE.MYCOL IS 'LABELONCOL'
```

The following query contains no AS CLAUSE:

```
SELECT MYCOL FROM MYTABLE
```

The following table lists the `ResultSetMetaData.getColumnName` and `ResultSetMetaData.getColumnName` values that are returned for the query.

Table 105. ResultSetMetaData.getColumnName and ResultSetMetaData.getColumnName before and after IBM Data Server Driver for JDBC and SQLJ Version 4.0 for a table column with a LABEL ON statement in a query with no AS CLAUSE

	Behavior before IBM Data Server Driver for JDBC and SQLJ Version 4.0		**Behavior for IBM Data Server Driver for JDBC and SQLJ Version 4.0**	
Target data source	**getColumnName value**	**getColumnLabel value**	**getColumnName value**	**getColumnLabel value**
Db2 for z/OS Version 8 or later, and Db2 for IBM i V5R3 and later	MYCOL	LABELONCOL	MYCOL	MYCOL
Db2 for z/OS Version 7, and Db2 for IBM i V5R2	MYCOL	LABELONCOL	MYLABEL	LABELONCOL

Error codes issued by the IBM Data Server Driver for JDBC and SQLJ

Warning codes in the ranges +4200 to +4299, and +4450 to +4499, and error codes in the ranges -4200 to -4299, and -4450 to -4499 are reserved for the IBM Data Server Driver for JDBC and SQLJ.

When you call the `SQLException.getMessage` method after a IBM Data Server Driver for JDBC and SQLJ error occurs, a string is returned that includes:

- Whether the connection is a type 2 or type 4 connection
- Diagnostic information for IBM Software Support
- The level of the driver
- An explanatory message
- The error code
- The SQLSTATE

For example:

```
[jcc][t4][20128][12071][3.50.54] Invalid queryBlockSize specified: 1,048,576,012.
Using default query block size of 32,767.  ERRORCODE=0, SQLSTATE=
```

The IBM Data Server Driver for JDBC and SQLJ issues the following warning codes:

+4204

Message text: Errors were encountered and tolerated as specified by the RETURN DATA UNTIL clause.

Explanation: Tolerated errors include federated connection, authentication, and authorization errors. This warning applies only to connections to Db2 on Linux, UNIX, and Windows systems servers. It is issued only when a cursor operation, such as a `ResultSet.next` or `ResultSet.previous` call, returns `false`.

SQLSTATE: 02506

+4222

Message text: *text-from-getMessage*

Explanation: A warning condition occurred during connection to the data source.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4223

Message text: *text-from-getMessage*

Explanation: A warning condition occurred during initialization.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4225

Message text and explanation: *text-from-getMessage*

Explanation: A warning condition occurred when data was sent to a server or received from a server.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4226

Message text and explanation: *text-from-getMessage*

Explanation: A warning condition occurred during customization or bind.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4228
Message text: *text-from-getMessage*

Explanation: An warning condition occurred that does not fit in another category.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4450
Message text: Feature not supported: *feature-name*

+4460
Message text: *text-from-getMessage*

Explanation: The specified value is not a valid option.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4461
Message text: *text-from-getMessage*

Explanation: The specified value is invalid or out of range.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4462
Message text: *text-from-getMessage*

Explanation: A required value is missing.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4470
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource is closed.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4471
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource is in use.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4472
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource is unavailable.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

+4474
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource cannot be changed.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

The IBM Data Server Driver for JDBC and SQLJ issues the following error codes:

-1224

Message text: The database manager is not able to accept new requests, has terminated all requests in progress, or has terminated the specified request because of an error or a forced interrupt.

Explanation: For connections to Db2 on Linux, UNIX, and Windows systems data servers, see SQL1224N for details.

For connections to Db2 for z/OS data servers, this error indicates the server thread that is associated with the application abnormally terminated. Server diagnostics that are related to the application need to be collected. The application can be identified by its unique application ID. Db2 for z/OS externalizes the application ID in messages and traces as the connection correlation token (CRRTKN) and logical unit of work ID (LUWID). Message DSNL027I is generated on the z/OS console when a Db2 for z/OS thread abnormally terminates. DSNL027I provides a reason code for the failure. In most cases, Db2 for z/OS generates a z/OS SVC dump, which is needed to solve the problem.

SQLSTATE: 2D521

-4200

Message text: Invalid operation: An invalid COMMIT or ROLLBACK has been called in an XA environment during a Global Transaction.

Explanation: An application that was in a global transaction in an XA environment issued a commit or rollback. A commit or rollback operation in a global transaction is invalid.

SQLSTATE: 2D521

-4201

Message text: Invalid operation: setAutoCommit(true) is not allowed during Global Transaction.

Explanation: An application that was in a global transaction in an XA environment executed the `setAutoCommit(true)` statement. Issuing `setAutoCommit(true)` in a global transaction is invalid.

SQLSTATE: 2D521

-4203

Message text: Error executing *function*. Server returned *rc*.

Explanation: An error occurred on an XA connection during execution of an SQL statement.

For network optimization, the IBM Data Server Driver for JDBC and SQLJ delays some XA flows until the next SQL statement is executed. If an error occurs in a delayed XA flow, that error is reported as part of the `SQLException` that is thrown by the current SQL statement.

-4210

Message text: Timeout getting a transport object from pool.

SQLSTATE: 57033

-4211

Message text: Timeout getting an object from pool.

SQLSTATE: 57033

-4212

Message text: Sysplex member unavailable.

-4213

Message text: Timeout.

SQLSTATE: 57033

-4214

Message text: *text-from-getMessage*

Explanation: Authorization failed.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

SQLSTATE: 28000

-4220

Message text: *text-from-getMessage*

Explanation: An error occurred during character conversion.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4221

Message text: *text-from-getMessage*

Explanation: An error occurred during encryption or decryption.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4222

Message text: *text-from-getMessage*

Explanation: An error occurred during connection to the data source.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4223

Message text: *text-from-getMessage*

Explanation: An error occurred during initialization.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4224

Message text: *text-from-getMessage*

Explanation: An error occurred during resource cleanup.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4225

Message text: *text-from-getMessage*

Explanation: An error occurred when data was sent to a server or received from a server.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4226

Message text: *text-from-getMessage*

Explanation: An error occurred during customization or bind.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4227

Message text: *text-from-getMessage*

Explanation: An error occurred during reset.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4228

Message text: *text-from-getMessage*

Explanation: An error occurred that does not fit in another category.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4229
Message text: *text-from-getMessage*

Explanation: An error occurred during a batch execution.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4231
Message text: An error occurred during the conversion of column *column-number* of type *sql-data-type* with value *value* to a value of type `java.math.BigDecimal`.

-4450
Message text: Feature not supported: *feature-name*

SQLSTATE: 0A504

-4460
Message text: *text-from-getMessage*

Explanation: The specified value is not a valid option.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4461
Message text: *text-from-getMessage*

Explanation: The specified value is invalid or out of range.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

SQLSTATE: 42815

-4462
Message text: *text-from-getMessage*

Explanation: A required value is missing.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4463
Message text: *text-from-getMessage*

Explanation: The specified value has a syntax error.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

SQLSTATE: 42601

-4470
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource is closed.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4471
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource is in use.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4472
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource is unavailable.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4473
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource is no longer available.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4474
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the target resource cannot be changed.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4475
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because access to the target resource is restricted.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4476
Message text: *text-from-getMessage*

Explanation: The requested operation cannot be performed because the operation is not allowed on the target resource.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

-4496
Message text: An SQL OPEN for a held cursor was issued on an XA connection. The JDBC driver does not allow a held cursor to be opened on the database server for an XA connection.

-4497
Message text: The application must issue a rollback. The unit of work has already been rolled back in the Db2 server, but other resource managers involved in the unit of work might not have rolled back their changes. To ensure integrity of the application, all SQL requests are rejected until the application issues a rollback.

-4498
Message text: A connection failed but has been re-established. Special register settings have been replayed if necessary. Host name or IP address of the connection: *host-name*. Service name or port number of the connection: *service-name*. Reason code: *reason-code*. Failure code: *failure-code*. Error code: *error-code*.

Explanation: The connection has been reestablished. In some cases, the network connection or transport to the server is not established until the next use. After the connection is reestablished, all session resources are set to their initial default values. The application is rolled back to the previous commit point. The reason code indicates which special register values are applied to the new connection. Possible values for the reason code are:

1
All special register settings were returned to their values at the point of failure. The connection was reestablished within the current group.

2
All special register settings were returned to their values at the previous commit point. The connection was reestablished within the current group.

3
All special registers were returned to their settings at the point of failure. The connection was reestablished in a new group.

4
All special register settings were returned to their values at the previous commit point. The connection was reestablished in a new group.

failure-code indicates the error that caused the connection to fail:

1
A communication failure occurred.

2
The data server closed the connection.

3
An SQL error occurred.

4
The client closed the connection.

error-code depends on the value of *failure-code*:

Failure code: 1 or 2
Error code: The Java `SocketException` message that was returned.

Failure code: 3
Error code: The SQL error code that was returned by the SQL statement that caused the connection to fail.

Failure code: 4
Error code: The following value:

2
The driver received an interrupt or cancel request.

For client reroute against Db2 for z/OS servers, special register values that were set after the last commit point are not re-established.

The application is rolled back to the previous commit point. The connection state and global resources such as global temporary tables and open held cursors might not be maintained.

-4499
Message text: *text-from-getMessage*

Explanation: A fatal error occurred that resulted in a disconnect from the data source. The existing connection has become unusable.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

SQLSTATE: 08001 or 58009

-20542
Message text: The statement was not executed because the connection to the database server was dropped, and the automatic client reroute (ACR) feature failed to successfully re-execute the statement.

Explanation: See SQL20542N.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

SQLSTATE: 54068

-30108

Message text: A connection failed in an automatic client reroute environment. The transaction was rolled back. Host name or IP address: *host-name*. Service name or port number: *service-name*. Reason code: *reason-code*. Connection failure code: *connection-failure-code*. Underlying error: *underlying-error*.

Explanation: See SQL30108N.

User response: Call `SQLException.getMessage` to retrieve specific information about the problem.

SQLSTATE: 08506

-99999

Message text: The IBM Data Server Driver for JDBC and SQLJ issued an error that does not yet have an error code.

Related tasks

"Handling SQL errors in an SQLJ application" on page 172
SQLJ clauses use the JDBC class `java.sql.SQLException` for error handling.

"Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ" on page 111
As in all Java programs, error handling for JDBC applications is done using `try/catch` blocks. Methods throw exceptions when an error occurs, and the code in the `catch` block handles those exceptions.

SQLSTATEs issued by the IBM Data Server Driver for JDBC and SQLJ

SQLSTATEs in the range 46600 to 466ZZ are reserved for the IBM Data Server Driver for JDBC and SQLJ.

The following table lists the SQLSTATEs that are generated or used by the IBM Data Server Driver for JDBC and SQLJ.

Table 106. SQLSTATEs returned by the IBM Data Server Driver for JDBC and SQLJ

SQLSTATE class	SQLSTATE	Description
01*xxx*		Warning
02*xxx*		No data
02*xxx*	02501	The cursor position is not valid for a FETCH of the current row.
02*xxx*	02506	Tolerable error
08*xxx*		Connection exception
08*xxx*	08001	The application requester is unable to establish the connection.
08*xxx*	08003	A connection does not exist
08*xxx*	08004	The application server rejected establishment of the connection
08*xxx*	08506	Client reroute exception
0A*xxx*		Feature not supported
0A*xxx*	0A502	The action or operation is not enabled for this database instance
0A*xxx*	0A504	The feature is not supported by the driver

Table 106. SQLSTATEs returned by the IBM Data Server Driver for JDBC and SQLJ (continued)

SQLSTATE class	SQLSTATE	Description
22*xxx*		Data exception
22*xxx*	22007	The string representation of a datetime value is invalid
22*xxx*	22021	A character is not in the coded character set
23*xxx*		Constraint violation
23*xxx*	23502	A value that is inserted into a column or updates a column is null, but the column cannot contain null values.
24*xxx*		Invalid cursor state
24*xxx*	24501	The identified cursor is not open
28*xxx*		Authorization exception
28*xxx*	28000	Authorization name is invalid.
2D*xxx*		Invalid transaction termination
2D*xxx*	2D521	SQL COMMIT or ROLLBACK are invalid in the current operating environment.
34*xxx*		Invalid cursor name
34*xxx*	34000	Cursor name is invalid.
3B*xxx*		Invalid savepoint
3B*xxx*	3B503	A SAVEPOINT, RELEASE SAVEPOINT, or ROLLBACK TO SAVEPOINT statement is not allowed in a trigger or global transaction.
40*xxx*		Transaction rollback
42*xxx*		Syntax error or access rule violation
42*xxx*	42601	A character, token, or clause is invalid or missing
42*xxx*	42734	A duplicate parameter name, SQL variable name, cursor name, condition name, or label was detected.
42*xxx*	42807	The INSERT, UPDATE, or DELETE is not permitted on this object
42*xxx*	42808	A column identified in the insert or update operation is not updateable
42*xxx*	42815	The data type, length, scale, value, or CCSID is invalid
42*xxx*	42820	A numeric constant is too long, or it has a value that is not within the range of its data type
42*xxx*	42968	The connection failed because there is no current software license.
57*xxx*		Resource not available or operator intervention
57*xxx*	57033	A deadlock or timeout occurred without automatic rollback
58*xxx*		System error
58*xxx*	58008	Execution failed due to a distribution protocol error that will not affect the successful execution of subsequent DDM commands or SQL statements

Table 106. SQLSTATEs returned by the IBM Data Server Driver for JDBC and SQLJ (continued)

SQLSTATE class	SQLSTATE	Description
58*xxx*	58009	Execution failed due to a distribution protocol error that caused deallocation of the conversation
58*xxx*	58012	The bind process with the specified package name and consistency token is not active
58*xxx*	58014	The DDM command is not supported
58*xxx*	58015	The DDM object is not supported
58*xxx*	58016	The DDM parameter is not supported
58*xxx*	58017	The DDM parameter value is not supported

Related tasks

"Handling SQL errors in an SQLJ application" on page 172
SQLJ clauses use the JDBC class `java.sql.SQLException` for error handling.

"Handling an SQLException under the IBM Data Server Driver for JDBC and SQLJ" on page 111
As in all Java programs, error handling for JDBC applications is done using `try/catch` blocks. Methods throw exceptions when an error occurs, and the code in the `catch` block handles those exceptions.

Commands for SQLJ program preparation

To prepare SQLJ programs for execution, you use commands to translate SQLJ source code into Java source code, compile the Java source code, create and customize SQLJ serialized profiles, and bind Db2 packages.

sqlj - SQLJ translator

The sqlj command translates an SQLJ source file into a Java source file and zero or more SQLJ serialized profiles. By default, the sqlj command also compiles the Java source file.

Authorization

None

Command syntax



Command parameters

-help
Specifies that the SQLJ translator describes each of the options that the translator supports. If any other options are specified with -help, they are ignored.

-dir=*directory*
Specifies the name of the directory into which SQLJ puts .java files that are generated by the translator and .class files that are generated by the compiler. The default is the directory that contains the SQLJ source files.

The translator uses the directory structure of the SQLJ source files when it puts the generated files in directories. For example, suppose that you want the translator to process two files:

- file1.sqlj, which is not in a Java package
- file2.sqlj, which is in Java package sqlj.test

Also suppose that you specify the parameter -dir=/src when you invoke the translator. The translator puts the Java source file for file1.sqlj in directory /src and puts the Java source file for file2.sqlj in directory /src/sqlj/test.

-d=*directory*
Specifies the name of the directory into which SQLJ puts the binary files that are generated by the translator and compiler. These files include the .ser files, the *name*_SJProfileKeys.class files, and the .class files that are generated by the compiler.

The default is the directory that contains the SQLJ source files.

The translator uses the directory structure of the SQLJ source files when it puts the generated files in directories. For example, suppose that you want the translator to process two files:

- file1.sqlj, which is not in a Java package
- file2.sqlj, which is in Java package sqlj.test

Also suppose that you specify the parameter -d=/src when you invoke the translator. The translator puts the serialized profiles for file1.sqlj in directory /src and puts the serialized profiles for file2.sqlj in directory /src/sqlj/test.

-compile=true|false
Specifies whether the SQLJ translator compiles the generated Java source into bytecodes.

true
The translator compiles the generated Java source code. This is the default.

false
The translator does not compile the generated Java source code.

-linemap=no|yes
Specifies whether line numbers in Java exceptions match line numbers in the SQLJ source file (the .sqlj file), or line numbers in the Java source file that is generated by the SQLJ translator (the .java file).

no
Line numbers in Java exceptions match line numbers in the Java source file. This is the default.

yes
Line numbers in Java exceptions match line numbers in the SQLJ source file.

-smap=no|yes
Specifies whether the SQLJ translator generates a source map (SMAP) file for each SQLJ source file. An SMAP file is used by some Java language debug tools. This file maps lines in the SQLJ source file to lines in the Java source file that is generated by the SQLJ translator. The file is in the Unicode UTF-8 encoding scheme. Its format is described by Original Java Specification Request (JSR) 45, which is available from this web site:

```
http://www.jcp.org
```

no
Do not generated SMAP files. This is the default.

yes
Generate SMAP files. An SMAP file name is *SQLJ-source-file-name*.java.smap. The SQLJ translator places the SMAP file in the same directory as the generated Java source file.

-encoding=*encoding-name*
Specifies the encoding of the source file. Examples are JIS or EUC. If this option is not specified, the default converter for the operating system is used.

-db2optimize
Specifies that the SQLJ translator generates code that enables SQLJ context caching in a WebSphere Application Server environment for applications that run against Db2 data servers.

-db2optimize causes a user-defined context to extend a custom driver class, which enables context caching and connection caching in WebSphere Application Server.

Because context caching is enabled by using an instance of IBM Data Server Driver for JDBC and SQLJ class `sqlj.runtime.ref.DefaultContext`, db2jcc4.jar must be in the CLASSPATH when you translate and compile the Java application.

You cannot use connection sharing in WebSphere Application Server if you use context caching.

Important: Context caching that is enabled by the -db2optimize option can provide performance benefits over connection pooling and statement pooling that is provided by WebSphere Application Server. However, context caching can result in significant resource consumption in the application server, and might have unintended side effects if it is not used correctly. For example, if two applications use an SQLJ profile with the same name, they might overwrite each other, because both use `sqlj.runtime.ref.DefaultContext`. Use context caching only if:

- The system is not storage-constrained.
- Cached statements are often reused on the same `Connection`.

- All applications have distinct names for their SQLJ profiles.

-ser2class
Specifies that the SQLJ translator converts .ser files to .class files.

-status
Specifies that the SQLJ translator displays status messages as it runs.

-version
Specifies that the SQLJ translator displays the version of the IBM Data Server Driver for JDBC and SQLJ. The information is in this form:

```
IBM SQLJ xxxx.xxxx.xx
```

-C-help
Specifies that the SQLJ translator displays help information for the Java compiler.

-C*compiler-option*
Specifies a valid Java compiler option that begins with a dash (-). Do not include spaces between -C and the compiler option. If you need to specify multiple compiler options, precede each compiler option with -C. For example:

```
-C-g -C-verbose
```

All options are passed to the Java compiler and are not used by the SQLJ translator, **except** for the following options:

-classpath
Specifies the user class path that is to be used by the SQLJ translator and the Java compiler. This value overrides the CLASSPATH environment variable.

-sourcepath
Specifies the source code path that the SQLJ translator and the Java compiler search for class or interface definitions. The SQLJ translator searches for .sqlj and .java files only in directories, not in JAR or zip files.

-JJVM-option
Specifies an option that is to be passed to the Java virtual machine (JVM) in which the sqlj command runs. The option must be a valid JVM option that begins with a dash (-). Do not include spaces between -J and the JVM option. If you need to specify multiple JVM options, precede each compiler option with -J. For example:

```
-J-Xmx128m -J-Xmine2M
```

SQLJ-source-file-name
Specifies a list of SQLJ source files to be translated. This is a required parameter. All SQLJ source file names must have the extension .sqlj.

Output

For each source file, *program-name*.sqlj, the SQLJ translator produces the following files:

- The generated source program

  The generated source file is named *program-name*.java.
- A serialized profile file for each connection context class that is used in an SQLJ executable clause

  A serialized profile name is of the following form:

  ```
  program-name_SJProfileIDNumber.ser
  ```
- If the SQLJ translator invokes the Java compiler, the class files that the compiler generates.

Examples

```
sqlj -encoding=UTF8 -C-O MyApp.sqlj
```

db2sqljcustomize - SQLJ profile customizer

db2sqljcustomize processes an SQLJ profile, which contains embedded SQL statements.

By default, db2sqljcustomize produces four Db2 packages: one for each isolation level. db2sqljcustomize augments the profile with information specific to Db2 for use at run time.

Authorization

The privilege set of the process must include one of the following authorities:

- SYSADM authority
- DBADM authority
- If the package does not exist, the BINDADD privilege, and one of the following privileges:
  - CREATEIN privilege
  - PACKADM authority on the collection or on all collections
- If the package exists, the BIND privilege on the package

Command syntax



Command parameters

-help
Specifies that the SQLJ customizer describes each of the options that the customizer supports. If any other options are specified with -help, they are ignored.

-url
Specifies the URL for the data server for which the profile is to be bound. The URL can be a URL for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity. A connection is established to the data source that this URL represents if the -automaticbind or -onlinecheck option is specified as YES or defaults to YES. The variable parts of the `-url` value are:

server
The domain name or IP address of the z/OS system on which the Db2 subsystem resides.

port
The TCP/IP server port number that is assigned to the Db2 subsystem. The default is 446.

-url
Specifies the URL for the data source for which the profile is to be customized. A connection is established to the data source that this URL represents if the -automaticbind or -onlinecheck option is specified as YES or defaults to YES. The variable parts of the `-url` value are:

server
The domain name or IP address of the operating system on which the database server resides.

port
The TCP/IP server port number that is assigned to the database server. The default is 446.

database
A name for the database server for which the profile is to be customized.

If the connection is to a Db2 for z/OS server, *database* is the Db2 location name that is defined during installation. All characters in this value must be uppercase characters. You can determine the location name by executing the following SQL statement on the server:

```
SELECT CURRENT SERVER FROM SYSIBM.SYSDUMMY1;
```

If the connection is to a Db2 on Linux, UNIX, and Windows systems server, *database* is the database name that is defined during installation.

If the connection is to an IBM Cloudscape server, the *database* is the fully-qualified name of the file that contains the database. This name must be enclosed in double quotation marks ("). For example:

```
"c:/databases/testdb"
```

***property=value*;**
A property for the JDBC connection.

***property=value*;**
A property for the JDBC connection.

-datasource *JNDI-name*
Specifies the logical name of a `DataSource` object that was registered with JNDI. The `DataSource` object represents the data source for which the profile is to be customized. A connection is established to the data source if the -automaticbind or -onlinecheck option is specified as YES or defaults to YES. Specifying -datasource is an alternative to specifying -url. The `DataSource` object must represent a connection that uses IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

-user *user-ID*
Specifies the user ID to be used to connect to the data source for online checking or binding a package. You must specify -user if you specify -url. You must specify -user if you specify -datasource, and the `DataSource` object that *JNDI-name* represents does not contain a user ID.

-password *password*
Specifies the password to be used to connect to the data source for online checking or binding a package. You must specify -password if you specify -url. You must specify -password if you specify -datasource, and the `DataSource` object that *JNDI-name* represents does not contain a password.

-automaticbind YES|NO
Specifies whether the customizer binds Db2 packages at the data source that is specified by the -url parameter.

The default is YES.

The number of packages and the isolation levels of those packages are controlled by the -rootpkgname and -singlepkgname options.

Before the bind operation can work, the following conditions need to be met:

- TCP/IP and DRDA must be installed at the target data source.
- Valid -url, -username, and -password values must be specified.
- The -username value must have authorization to bind a package at the target data source.

-pkgversion AUTO|*version-id*
Specifies the package version that is to be used when packages are bound at the server for the serialized profile that is being customized. db2sqljcustomize stores the version ID in the serialized profile and in the Db2 package. Run-time version verification is based on the consistency token, not the version name. To automatically generate a version name that is based on the consistency token, specify -pkgversion AUTO.

The default is that there is no version.

-bindoptions *options-string*
Specifies a list of options, separated by spaces. These options have the same function as Db2 precompile and bind options with the same names. If you are preparing your program to run on a Db2 for z/OS system, specify z/OS options. If you are preparing your program to run on a Db2 on Linux, UNIX, and Windows systems system, specify Db2 on Linux, UNIX, and Windows systems options.

Notes on bind options:

- Specify ISOLATION only if you also specify the -singlepkgname option.

Important: Specify only those program preparation options that are appropriate for the data source at which you are binding a package. Some values and defaults for the IBM Data Server Driver for JDBC and SQLJ are different from the values and defaults for Db2.

-storebindoptions
Specifies that values for the -bindoptions and -staticpositioned parameters are stored in the serialized profile. If db2sqljbind is invoked without the -bindoptions or -staticpositioned parameter, the values that are stored in the serialized profile are used during the bind operation. When multiple serialized profiles are specified for one invocation of db2sqljcustomize, the parameter values are stored in each serialized profile. The stored values are displayed in the output from the db2sqljprint utility.

-collection *collection-name*
The qualifier for the packages that `db2sqljcustomize` binds. `db2sqljcustomize` stores this value in the customized serialized profile, and it is used when the associated packages are bound. If you do not specify this parameter, `db2sqljcustomize` uses a collection ID of NULLID.

-onlinecheck YES|NO
Specifies whether online checking of data types in the SQLJ program is to be performed. The -url or -datasource option determines the data source that is to be used for online checking. The default is YES if the -url or -datasource parameter is specified. Otherwise, the default is NO.

Online checking is performed only when db2sqljcustomize is invoked. No online checking is performed when SQL statements are executed at run time.

-onTypeMismatch WARN|EXP_EXIT|EXP_CONT|NOACC
Specifies the action that the IBM Data Server Driver for JDBC and SQLJ takes when there is a mismatch between a host variable data type and the data type of the column to which the host variable is bound. Possible values are:

WARN
The driver issues a warning. This value is the default.

EXP_EXIT
The driver throws an exception, and db2sqljcustomize terminates.

EXP_CONT
The driver throws an exception, and db2sqljcustomize continues.

NOACC
The driver takes no action.

-onTypeMismatch applies to version 4.33 or later of the IBM Data Server Driver for JDBC and SQLJ. Before version 4.33, the driver takes no action when there is a data type mismatch.

-qualifier *qualifier-name*
Specifies the qualifier that is to be used for unqualified objects in the SQLJ program during online checking. This value is not used as the qualifier when the packages are bound.

-rootpkgname|-singlepkgname
Specifies the names for the packages that are associated with the program. If -automaticbind is NO, these package names are used when `db2sqljbind` runs. The meanings of the parameters are:

-rootpkgname *package-name-stem*
Specifies that the customizer creates four packages, one for each of the four Db2 isolation levels. The names for the four packages are:

***package-name-stem*1**
For isolation level UR

***package-name-stem*2**
For isolation level CS

***package-name-stem*3**
For isolation level RS

***package-name-stem*4**
For isolation level RR

If -longpkgname is not specified, *package-name-stem* must be an alphanumeric string of seven or fewer bytes.

If -longpkgname is specified, *package-name-stem* must be an alphanumeric string of 127 or fewer bytes.

-singlepkgname *package-name*
Specifies that the customizer creates one package, with the name *package-name*. If you specify this option, your program can run at only one isolation level. You specify the isolation level for the package by specifying the ISOLATION option in the -bindoptions options string.

If -longpkgname is not specified, *package-name* must be an alphanumeric string of eight or fewer bytes.

If -longpkgname is specified, *package-name* must be an alphanumeric string of 128 or fewer bytes.

Using the -singlepkgname option is not recommended.

Recommendation: If the target data source is Db2 for z/OS, use uppercase characters for the *package-name-stem* or *package-name* value. Db2 for z/OS systems that are defined with certain CCSID values cannot tolerate lowercase characters in package names or collection names.

If you do not specify -rootpkgname or -singlepkgname, db2sqljcustomize generates four package names that are based on the serialized profile name. A serialized profile name is of the following form:

```
program-name_SJProfileIDNumber.ser
```

The four generated package names are of the following form:

```
Bytes-from-program-nameIDNumberPkgIsolation
```

Table 107 on page 521 shows the parts of a generated package name and the number of bytes for each part.

The maximum length of a package name is *maxlen*. *maxlen* is 8 if -longpkgname is not specified. *maxlen* is 128 if -longpkgname is specified.

Table 107. Parts of a package name that is generated by db2sqljcustomize

Package name part	Number of bytes	Value
Bytes-from-program-name	*m*=min(Length(*program-name*), *maxlen*–1–Length(*IDNumber*))	First *m* bytes of *program-name*, in uppercase
IDNumber	Length(*IDNumber*)	*IDNumber*
PkgIsolation	1	1, 2, 3, or 4. This value represents the transaction isolation level for the package. See Table 108 on page 521.

Table 108 on page 521 shows the values of the *PkgIsolation* portion of a package name that is generated by db2sqljcustomize.

Table 108. PkgIsolation values and associated isolation levels

***PkgNumber* value**	**Isolation level for package**
1	Uncommitted read (UR)
2	Cursor stability (CS)
3	Read stability (RS)
4	Repeatable read (RR)

Example: Suppose that a profile name is ThisIsMyProg_SJProfile111.ser. The db2sqljcustomize option -longpkgname is not specified. Therefore, *Bytes-from-program-name* is the first four bytes of ThisIsMyProg, translated to uppercase, or THIS. *IDNumber* is 111. The four package names are:

```
THIS1111
THIS1112
THIS1113
THIS1114
```

Example: Suppose that a profile name is ThisIsMyProg_SJProfile111.ser. The db2sqljcustomize option -longpkgname is specified. Therefore, *Bytes-from-program-name* is ThisIsMyProg, translated to uppercase, or THISISMYPROG. *IDNumber* is 111. The four package names are:

```
THISISMYPROG1111
THISISMYPROG1112
THISISMYPROG1113
THISISMYPROG1114
```

Example: Suppose that a profile name is A_SJProfile0.ser. *Bytes-from-program-name* is A. *IDNumber* is 0. Therefore, the four package names are:

```
A01
A02
A03
A04
```

Letting `db2sqljcustomize` generate package names is not recommended. If any generated package names are the same as the names of existing packages, `db2sqljcustomize` overwrites the existing packages. To ensure uniqueness of package names, specify -rootpkgname.

-longpkgname
Specifies that the names of the Db2 packages that db2sqljcustomize generates can be up to 128 bytes. Use this option only if you are binding packages at a server that supports long package names. If you specify -singlepkgname or -rootpkgname, you must also specify -longpkgname under the following conditions:

- The argument of -singlepkgname is longer than eight bytes.
- The argument of -rootpkgname is longer than seven bytes.

-staticpositioned NO|YES
For iterators that are declared in the same source file as positioned UPDATE statements that use the iterators, specifies whether the positioned UPDATEs are executed as statically bound statements. The default is NO. NO means that the positioned UPDATEs are executed as dynamically prepared statements.

-zosDescProcParms
Specifies that db2sqljcustomize queries the Db2 catalog at the target data source to determine the SQL parameter data types that correspond to the host variables in CALL statements.

-zosDescProcParms applies only to programs that run on Db2 for z/OS data servers.

If -zosDescProcParms is specified, and the authorization ID under which db2sqljcustomize runs does not have read access to the SYSIBM.SYSROUTINES catalog table, db2sqljcustomize returns an error and uses the host variable data types in the CALL statements to determine the SQL data types.

Specification of -zosDescProcParms can lead to more efficient storage usage at run time. If SQL data type information is available, SQLJ has information about the length and precision of INOUT and OUT parameters, so it allocates only the amount of memory that is needed for those parameters. Availability of SQL data type information can have the biggest impact on storage usage for character INOUT parameters, LOB OUT parameters, and decimal OUT parameters.

When -zosDescProcParms is specified, the Db2 data server uses the specified or default value of -zosProcedurePath to resolve unqualified names of stored procedures for which SQL data type information is requested.

If -zosDescProcParms is not specified, db2sqljcustomize uses the host variable data types in the CALL statements to determine the SQL data types. If db2sqljcustomize determines the wrong SQL data type, an SQL error might occur at run time. For example, if the Java host variable type is String, and the corresponding stored procedure parameter type is VARCHAR FOR BIT DATA, an SQL run-time error such as -4220 might occur.

-zosProcedurePath *procedure-path*
Specifies a list of schema names that Db2 for z/OS uses to resolve unqualified stored procedure names during online checking of an SQLJ program.

-zosProcedurePath applies to programs that are to be run on Db2 for z/OS database servers only.

The list is a String value that is a comma-separated list of schema names that is enclosed in double quotation marks. The Db2 database server inserts that list into the SQL path for resolution of unqualified stored procedure names. The SQL path is:

```
SYSIBM, SYSFUN, SYSPROC, procedure-path, qualifier-name, user-ID
```

qualifier-name is the value of the -qualifier parameter, and *user-ID* is the value of the -user parameter.

The Db2 data server tries the schema names in the SQL path from left to right until it finds a match with the name of a stored procedure that exists on that database server. If the data server finds a match, it obtains the information about the parameters for that stored procedure from the Db2 catalog. If the Db2 data server does not find a match, SQLJ sets the parameter data without any Db2 catalog information.

If -zosProcedurePath is not specified, the Db2 data server uses this SQL path:

```
SYSIBM, SYSFUN, SYSPROC, qualifier-name, user-ID
```

If the -qualifier parameter is not specified, the SQL path does not include *qualifier-name*.

-genDBRM
Specifies that db2sqljcustomize generates database request modules (DBRMs). Those DBRMs can be used to create Db2 for z/OS packages.

-genDBRM applies to programs that are to be run on Db2 for z/OS database servers only.

If -genDBRM and -automaticbind NO are specified, db2sqljcustomize creates the DBRMs but does not bind them into Db2 packages. If -genDBRM and -automaticbind YES are specified, db2sqljcustomize creates the DBRMs and binds them into Db2 packages.

One DBRM is created for each Db2 isolation level. The naming convention for the generated DBRM files is the same as the naming convention for packages. For example, if -rootpkgname SQLJSA0 is specified, and -genDBRM is also specified, the names of the four DBRM files are:

- SQLJSA01
- SQLJSA02
- SQLJSA03
- SQLJSA04

-hostLangJAVA
When **-genDBRM** is specified, the **-hostLangJAVA** option specifies that the db2sqljcustomize process should create DBRM files that identify their host language as 'J'. When these DBRMs are bound into Db2 packages, the corresponding HOSTLANG column in the SYSIBM.SYSPACKAGE table is set to 'J'. This identifies packages that were generated with the Java language. This option is only available for Db2 for z/OS v11 and above.

-DBRMDir *directory-name*
When -genDBRM is specified, -DBRMDir specifies the local directory into which db2sqljcustomize puts the generated DBRM files. The default is the current directory.

-DBRMdir applies to programs that are to be run on Db2 for z/OS database servers only.

-tracefile *file-name*
Enables tracing and identifies the output file for trace information. This option should be specified only under the direction of IBM Software Support.

-tracelevel
If -tracefile is specified, indicates what to trace while `db2sqljcustomize` runs. The default is TRACE_SQLJ. This option should be specified only under the direction of IBM Software Support.

***serialized-profile-name*|*file-name*.grp**
Specifies the names of one or more serialized profiles that are to be customized. The specified serialized profile must be in a directory that is named in the CLASSPATH environment variable.

A serialized profile name is of the following form:

```
program-name_SJProfileIDNumber.ser
```

You can specify the serialized profile name with or without the .ser extension.

program-name is the name of the SQLJ source program, without the extension .sqlj. *n* is an integer between 0 and *m-1*, where *m* is the number of serialized profiles that the SQLJ translator generated from the SQLJ source program.

You can specify serialized profile names in one of the following ways:

- List the names in the db2sqljcustomize command. Multiple serialized profile names must be separated by spaces.
- Specify the serialized profile names, one on each line, in a file with the name *file-name*.grp, and specify *file-name*.grp in the db2sqljcustomize command.

If you specify more than one serialized profile name, and if you specify or use the default value of -automaticbind YES, db2sqljcustomize binds a single Db2 package from the profiles. When you use db2sqljcustomize to create a single Db2 package from multiple serialized profiles, you must also specify the -rootpkgname or -singlepkgname option.

If you specify more than one serialized profile name, and you specify -automaticbind NO, if you want to bind the serialized profiles into a single Db2 package when you run db2sqljbind, you need to specify the same list of serialized profile names, in the same order, in db2sqljcustomize and db2sqljbind.

If you specify one or more *file-name*.grp files, and you specify -automaticbind NO, when you run db2sqljbind, you must specify that same list of files, and in the same order in which the files were customized.

You cannot run db2sqljcustomize on individual files, and then group those files when you run db2sqljbind.

Output

When `db2sqljcustomize` runs, it creates a customized serialized profile. It also creates Db2 packages, if the automaticbind value is YES.

Examples

```
db2sqljcustomize -user richler -password mordecai
  -url jdbc:db2://server:50000/sample -collection duddy
  -bindoptions "EXPLAIN YES" pgmname_SJProfile0.ser
```

The following example demonstrates passing the **hostLangJAVA** option to the customizer, and binding a package on a Db2 for z/OS server:

```
db2sqljcustomize -user richler -password mordecai
     -url jdbc:db2://server:446/sample -genDBRM -DBRMDir /dbrmdir/
     -hostLangJAVA  pgmname_SJProfile0.ser
```

Usage notes

Online checking is always recommended: It is highly recommended that you use online checking when you customize your serialized profiles. Online checking determines information about the data types and lengths of Db2 host variables, and is especially important for the following items:

- Predicates with java.lang.String host variables and CHAR columns

  Unlike character variables in other host languages, Java String host variables are not declared with a length attribute. To optimize a query properly that contains character host variables, Db2 needs the length of the host variables. For example, suppose that a query has a predicate in which a String host variable is compared to a CHAR column, and an index is defined on the CHAR column. If Db2 cannot determine the length of the host variable, it might do a table space scan instead of an index scan. Online checking avoids this problem by providing the lengths of the corresponding character columns.
- Predicates with java.lang.String host variables and GRAPHIC columns

Without online checking, Db2 might issue a bind error (SQLCODE -134) when it encounters a predicate in which a String host variable is compared to a GRAPHIC column.

- Column names in the result table of an SQLJ SELECT statement at a remote server:

  Without online checking, the driver cannot determine the column names for the result table of a remote SELECT.

Customizing multiple serialized profiles together: Multiple serialized profiles can be customized together to create a single Db2 package. If you do this, and if you specify -staticpositioned YES, any positioned UPDATE or DELETE statement that references a cursor that is declared *earlier in the package* executes statically, even if the UPDATE or DELETE statement is in a different source file from the cursor declaration. If you want -staticpositioned YES behavior when your program consists of multiple source files, you need to order the profiles in the db2sqljcustomize command to cause cursor declarations to be ahead of positioned UPDATE or DELETE statements in the package. To do that, list profiles that contain SELECT statements that assign result tables to iterators *before* profiles that contain the positioned UPDATE or DELETE statements that reference those iterators.

Using a customized serialized profile at one data source that was customized at another data source: You can run `db2sqljcustomize` to produce a customized serialized profile for an SQLJ program at one data source, and then use that profile at another data source. You do this by running `db2sqljbind` multiple times on customized serialized profiles that you created by running `db2sqljcustomize` once. When you run the programs at these data sources, the Db2 objects that the programs access must be identical at every data source. For example, tables at all data sources must have the same encoding schemes and the same columns with the same data types.

Using the -collection parameter: `db2sqljcustomize` stores the Db2 collection name in each customized serialized profile that it produces. When an SQLJ program is executed, the driver uses the collection name that is stored in the customized serialized profile to search for packages to execute. The name that is stored in the customized serialized profile is determined by the value of the -collection parameter. Only one collection ID can be stored in the serialized profile. However, you can bind the same serialized profile into multiple package collections by specifying the COLLECTION option in the -bindoptions parameter. To execute a package that is in a collection other than the collection that is specified in the serialized profile, include a SET CURRENT PACKAGESET statement in the program.

Using the VERSION parameter: Use the VERSION parameter to bind two or more versions of a package for the same SQLJ program into the same collection. You might do this if you have changed an SQLJ source program, and you want to run the old and new versions of the program.

To maintain two versions of a package, follow these steps:

1. Change the code in your source program.
2. Translate the source program to create a new serialized profile. Ensure that you do not overwrite your original serialized profile.
3. Run `db2sqljcustomize` to customize the serialized profile and create Db2 packages with the same package names and in the same collection as the original packages. Do this by using the same values for -rootpkgname and -collection when you bind the new packages that you used when you created the original packages. Specify the VERSION option in the -bindoptions parameter to put a version ID in the new customized serialized profile and in the new packages.

   It is essential that you specify the VERSION option when you perform this step. If you do not, you overwrite your original packages.

When you run the old version of the program, Db2 loads the old versions of the packages. When you run the new version of the program, Db2 loads the new versions of the packages.

Binding packages and plans on Db2 for z/OS: You can use the db2sqljcustomize -genDBRM parameter to create DBRMs on your local system. You can then transfer those DBRMs to a Db2 for z/OS system, and bind them into packages there. If you plan to use this technique, you need to transfer the DBRM files to the z/OS system as **binary** files, to a partitioned data set with record format FB and record length 80. When you bind the packages, you need to specify the following bind option values:

ENCODING(EBCDIC)
The IBM Data Server Driver for JDBC and SQLJ on Db2 for z/OS requires EBCDIC encoding for your packages.

DYNAMICRULES(BIND)
This option ensures consistent authorization rules when SQLJ uses dynamic SQL. SQLJ uses dynamic SQL for positioned UPDATE or DELETE operations that involve multiple SQLJ programs.

EXTENDEDINDICATOR bind option behavior: If the EXTENDEDINDICATOR bind option is not specified in the -bindoptions options string, and the target data server supports extended indicators, bind operations use EXTENDEDINDICATOR(YES). If EXTENDEDINDICATOR(NO) is explicitly specified, and the application contains extended indicator syntax, unexpected behavior can occur because the IBM Data Server Driver for JDBC and SQLJ treats extended indicators as NULL values.

Related reference
BIND and REBIND options for packages, plans, and services (Db2 Commands)

db2sqljbind - SQLJ profile binder

db2sqljbind binds Db2 packages for a serialized profile that was previously customized with the db2sqljcustomize command.

Applications that run with the IBM Data Server Driver for JDBC and SQLJ require packages but no plans. If the db2sqljcustomize -automaticbind option is specified as YES or defaults to YES, db2sqljcustomize binds packages for you at the data source that you specify in the -url parameter. However, if -automaticbind is NO, if a bind fails when db2sqljcustomize runs, or if you want to create identical packages at multiple locations for the same serialized profile, you can use the db2sqljbind command to bind packages.

Authorization

The privilege set of the process must include one of the following authorities:

- SYSADM authority
- DBADM authority
- If the package does not exist, the BINDADD privilege, and one of the following privileges:
  - CREATEIN privilege
  - PACKADM authority on the collection or on all collections
- If the package exists, the BIND privilege on the package

Command syntax



Command parameters

-help
Specifies that db2sqljbind describes each of the options that it supports. If any other options are specified with -help, they are ignored.

-url
Specifies the URL for the data server for which the profile is to be bound. The URL can be a URL for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity. The variable parts of the -url value are:

server
The domain name or IP address of the operating system on which the database server resides.

port
The TCP/IP server port number that is assigned to the database server. The default is 446.

database
A name for the database server for which the profile is to be customized.

If the connection is to a Db2 for z/OS server, *database* is the Db2 location name that is defined during installation. All characters in this value must be uppercase characters. You can determine the location name by executing the following SQL statement on the server:

```
SELECT CURRENT SERVER FROM SYSIBM.SYSDUMMY1;
```

If the connection is to a Db2 on Linux, UNIX, and Windows systems server, *database* is the database name that is defined during installation.

If the connection is to an IBM Cloudscape server, the *database* is the fully-qualified name of the file that contains the database. This name must be enclosed in double quotation marks ("). For example:

```
"c:/databases/testdb"
```

***property=value*;**
A property for the JDBC connection.

-datasource *JNDI-name*
Specifies the logical name of a DataSource object that was registered with JNDI. The DataSource object represents the data source for which the profile is to be customized. A connection is established to the data source if the -automaticbind or -onlinecheck option is specified as YES or defaults to YES. Specifying -datasource is an alternative to specifying -url. The DataSource object must represent a connection that uses IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

-user *user-ID*
Specifies the user ID to be used to connect to the data source for binding the package.

-password *password*
Specifies the password to be used to connect to the data source for binding the package.

-bindoptions *options-string*
Specifies a list of options, separated by spaces. These options have the same function as Db2 precompile and bind options with the same names. If you are preparing your program to run on a Db2 for z/OS system, specify z/OS options. If you are preparing your program to run on a Db2 on Linux, UNIX, and Windows systems system, specify Db2 on Linux, UNIX, and Windows systems options.

Notes on bind options:

- Specify VERSION only if the following conditions are true:
  - If you are binding a package at a Db2 on Linux, UNIX, and Windows systems system, the system is at Version 8 or later.
  - You rerun the translator on a program before you bind the associated package with a new VERSION value.

Important: Specify only those program preparation options that are appropriate for the data source at which you are binding a package. Some values and defaults for the IBM Data Server Driver for JDBC and SQLJ are different from the values and defaults for Db2.

-staticpositioned NO|YES
For iterators that are declared in the same source file as positioned UPDATE statements that use the iterators, specifies whether the positioned UPDATEs are executed as statically bound statements. The default is NO. NO means that the positioned UPDATEs are executed as dynamically prepared statements. This value must be the same as the -staticpositioned value for the previous db2sqljcustomize invocation for the serialized profile.

-genDBRM
Specifies that db2sqljbind generates database request modules (DBRMs) from the serialized profile, and that db2sqljbind does not perform remote bind operations.

-genDBRM applies to programs that are to be run on Db2 for z/OS database servers only.

-DBRMDir *directory-name*
When -genDBRM is specified, -DBRMDir specifies the local directory into which db2sqljbind puts the generated DBRM files. The default is the current directory.

-DBRMdir applies to programs that are to be run on Db2 for z/OS database servers only.

-tracefile *file-name*
Enables tracing and identifies the output file for trace information. This option should be specified only under the direction of IBM Software Support.

-tracelevel
If -tracefile is specified, indicates what to trace while `db2sqljcustomize` runs. The default is TRACE_SQLJ. This option should be specified only under the direction of IBM Software Support.

***serialized-profile-name*|*file-name*.grp**
Specifies the names of one or more serialized profiles from which the package is bound. A serialized profile name is of the following form:

```
program-name_SJProfileIDNumber.ser
```

program-name is the name of the SQLJ source program, without the extension .sqlj. *n* is an integer between 0 and *m-1*, where *m* is the number of serialized profiles that the SQLJ translator generated from the SQLJ source program.

You can specify serialized profile names in one of the following ways:

- List the names in the db2sqljcustomize command. Multiple serialized profile names must be separated by spaces.
- Specify the serialized profile names, one on each line, in a file with the name *file-name*.grp, and specify *file-name*.grp in the db2sqljbind command.

If you specify more than one serialized profile name to bind a single Db2 package from several serialized profiles, you must have specified the same serialized profile names, in the same order, when you ran db2sqljcustomize.

If you specify one or more *file-name*.grp files, you must have run db2sqljcustomize once with that same list of files. The order in which you specify the files in db2sqljbind must be the same as the order in db2sqljcustomize.

You cannot run db2sqljcustomize on individual files, and then group those files when you run db2sqljbind.

Examples

```
db2sqljbind -user richler -password mordecai
  -url jdbc:db2://server:50000/sample -bindoptions "EXPLAIN YES"
  pgmname_SJProfile0.ser
```

Usage notes

Package names produced by db2sqljbind: The names of the packages that are created by `db2sqljbind` are the names that you specified using the-rootpkgname or -singlepkgname parameter when you ran `db2sqljcustomize`. If you did not specify -rootpkgname or -singlepkgname, the package names are the first seven bytes of the profile name, appended with the isolation level character.

DYNAMICRULES value for db2sqljbind: The DYNAMICRULES bind option determines a number of run-time attributes for the Db2 package. Two of those attributes are the authorization ID that is used to check authorization, and the qualifier that is used for unqualified objects. To ensure the correct authorization for dynamically executed positioned UPDATE and DELETE statements in SQLJ programs, `db2sqljbind` always binds the Db2 packages with the DYNAMICRULES(BIND) option. You cannot modify this option. The DYNAMICRULES(BIND) option causes the SET CURRENT SQLID statement to have no impact on an SQLJ program, because those statements affect only dynamic statements that are bound with DYNAMICRULES values other than BIND.

With DYNAMICRULES(BIND), unqualified table, view, index, and alias names in dynamic SQL statements are implicitly qualified with value of the bind option QUALIFIER. If you do not specify QUALIFIER, Db2 uses the authorization ID of the package owner as the implicit qualifier. If this behavior is not suitable for your program, you can use one of the following techniques to set the correct qualifier:

- Force positioned UPDATE and DELETE statements to execute statically. You can use the -staticpositioned YES option of db2sqljcustomize or db2sqljbind to do this if the cursor (iterator) for a positioned UPDATE or DELETE statement is in the same package as the positioned UPDATE or DELETE statement.
- Fully qualify Db2*ƒ* table names in positioned UPDATE and positioned DELETE statements.

EXTENDEDINDICATOR bind option behavior: If the EXTENDEDINDICATOR bind option is not specified in the -bindoptions options string, and the target data server supports extended indicators, bind operations use EXTENDEDINDICATOR(YES). If EXTENDEDINDICATOR(NO) is explicitly specified, and the application contains extended indicator syntax, unexpected behavior can occur because the IBM Data Server Driver for JDBC and SQLJ treats extended indicators as NULL values.

Related reference
BIND and REBIND options for packages, plans, and services (Db2 Commands)

db2sqljprint - SQLJ profile printer

db2sqljprint prints the contents of the customized version of a profile as plain text.

Authorization

None

Command syntax



Command parameters

profilename
Specifies the relative or absolute name of an SQLJ profile file. When an SQLJ file is translated into a Java source file, information about the SQL operations it contains is stored in SQLJ-generated resource files called profiles. Profiles are identified by the suffix _SJProfileN (where N is an integer) following the name of the original input file. They have a `.ser` extension. Profile names can be specified with or without the `.ser` extension.

Examples

```
db2sqljprint pgmname_SJProfile0.ser
```

Chapter 9. Installing the IBM Data Server Driver for JDBC and SQLJ on Db2 for z/OS

After you install Db2 for z/OS or migrate to the current version of Db2 for z/OS, you need to install the current version of the IBM Data Server Driver for JDBC and SQLJ.

Installing the IBM Data Server Driver for JDBC and SQLJ as part of a Db2 installation

Installation of the IBM Data Server Driver for JDBC and SQLJ on your Db2 subsystem allows you to build and run Java database applications.

Before you begin

Prerequisites for the IBM Data Server Driver for JDBC and SQLJ:

- An SDK for Java

  To find the minimum required Java Software Development kit (SDK) version for Db2 12, see Program directories for Db2 12 (Db2 for z/OS in IBM Documentation).

  The IBM Data Server Driver for JDBC and SQLJ supports 31-bit or 64-bit Java applications.

  For stand-alone applications that require a 64-bit JVM, you need to install the IBM 64-bit SDK for z/OS, Java 2 Technology Edition, V5 or later.

  For Java stored procedures and user-defined functions that require a 64-bit JVM, you need to install the IBM 64-bit SDK for z/OS, Java 2 Technology Edition, V6 or later.
- TCP/IP

  TCP/IP is required on the client and all database servers to which you connect.
- Db2 for z/OS distributed data facility (DDF) and TCP/IP support.
- Unicode support for OS/390® and z/OS servers.

Procedure

To install the IBM Data Server Driver for JDBC and SQLJ, follow these steps:

1. When you allocate and load the Db2 for z/OS libraries, include the steps that allocate and load the IBM Data Server Driver for JDBC and SQLJ libraries.

   See “Jobs for loading the IBM Data Server Driver for JDBC and SQLJ libraries” on page 534 for details.
2. On Db2 for z/OS, set subsystem parameter DESCSTAT to YES. DESCSTAT corresponds to installation field DESCRIBE FOR STATIC on panel DSNTIPF. This step is necessary for SQLJ support.

   See DESCRIBE FOR STATIC field (DESCSTAT subsystem parameter) (Db2 Installation and Migration) for details.
3. In z/OS UNIX System Services, edit your .profile file to customize the environment variable settings. You use this step to set the libraries, paths, and files that the IBM Data Server Driver for JDBC and SQLJ uses.

   You also use this step to indicate the versions of JDBC and SQLJ support that you need.

   See “Environment variables for the IBM Data Server Driver for JDBC and SQLJ” on page 534 for details.
4. **Optional:** Customize the IBM Data Server Driver for JDBC and SQLJ configuration properties.

© Copyright IBM Corp. 1998, 2017

See "Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 536 for details.

5. On Db2 for z/OS, enable the Db2 supplied stored procedures and define the tables that are used by the IBM Data Server Driver for JDBC and SQLJ.

   See "Enabling the Db2-supplied stored procedures used by the IBM Data Server Driver for JDBC and SQLJ" on page 537 for details.

6. In z/OS UNIX System Services, run the DB2Binder utility to bind the packages for the IBM Data Server Driver for JDBC and SQLJ.

   See "DB2Binder utility" on page 539 for details.

7. Verify the installation by running a simple JDBC application.

   See "Verify the installation of the IBM Data Server Driver for JDBC and SQLJ" on page 548 for details.

Related concepts

Connecting distributed database systems (Db2 Installation and Migration)

Related tasks

Connecting Db2 for z/OS distributed database systems with TCP/IP (Db2 Installation and Migration)

Related reference

DESCRIBE FOR STATIC field (DESCSTAT subsystem parameter) (Db2 Installation and Migration)

Jobs for loading the IBM Data Server Driver for JDBC and SQLJ libraries

When you install Db2 for z/OS, allocate the HFS or zFS directory structure, and use SMP/E to load the IBM Data Server Driver for JDBC and SQLJ libraries.

The following jobs perform those functions.

DSNISMKD
Invokes the DSNMKDIR EXEC to allocate the HFS or zFS directory structures.

DSNDDEF1
Includes steps to define DDDEFs for the IBM Data Server Driver for JDBC and SQLJ libraries.

DSNRECV3
Includes steps that perform the SMP/E RECEIVE function for the IBM Data Server Driver for JDBC and SQLJ libraries.

DSNAPPL1
Includes the steps that perform the SMP/E APPLY CHECK and APPLY functions for the IBM Data Server Driver for JDBC and SQLJ libraries.

DSNACEP1
Includes the steps that perform the SMP/E ACCEPT CHECK and ACCEPT functions for the IBM Data Server Driver for JDBC and SQLJ libraries.

See *IBM Db2 for z/OS Program Directory* for information on allocating and loading Db2 data sets.

Environment variables for the IBM Data Server Driver for JDBC and SQLJ

If you set specific environment variables, the operating system can locate the IBM Data Server Driver for JDBC and SQLJ.

The environment variables that you must set are:

STEPLIB
Modify STEPLIB to include the SDSNEXIT, SDSNLOAD, and SDSNLOD2 data sets. For example:

```
export STEPLIB=DSNC10.SDSNEXIT:DSNC10.SDSNLOAD:DSNC10.SDSNLOD2:$STEPLIB
```

PATH
Modify PATH to include the directory that contains the shell scripts that invoke IBM Data Server Driver for JDBC and SQLJ program preparation and debugging functions.

For example, if the IBM Data Server Driver for JDBC and SQLJ is installed in `/usr/lpp/db2c10/jdbc`, modify PATH as follows:

```
export PATH=/usr/lpp/db2c10/jdbc/bin:$PATH
```

LIBPATH

The IBM Data Server Driver for JDBC and SQLJ contains the following dynamic load libraries (DLLs):

- libdb2jcct2zos.so
- libdb2jcct2zos_64.so

Those DLLs contain the native (C or C++) implementation of the IBM Data Server Driver for JDBC and SQLJ. The driver uses this code when you use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

Modify LIBPATH to include the directory that contains these DLLs.

For example, if the IBM Data Server Driver for JDBC and SQLJ is installed in `/usr/lpp/db2c10/jdbc`, modify LIBPATH as follows:

```
export LIBPATH=/usr/lpp/db2c10/jdbc/lib:$LIBPATH
```

CLASSPATH

The IBM Data Server Driver for JDBC and SQLJ contains the following class files:

`db2jcc4.jar`
Contains all JDBC classes and the SQLJ runtime classes for the IBM Data Server Driver for JDBC and SQLJ.

Include db2jcc4.jar in the CLASSPATH to indicate that you are using the version of the IBM Data Server Driver for JDBC and SQLJ that includes **JDBC 4.0 and later functions, as well as JDBC 3.0 and earlier functions.**

`sqlj4.zip`
Contains the classes that are needed to prepare SQLJ applications for execution under the IBM Data Server Driver for JDBC and SQLJ.

Include sqlj4.zip in the CLASSPATH to indicate that you plan to prepare SQLJ applications that include **JDBC 4.0 and later functions, as well as JDBC 3.0 and earlier functions.**

`db2jcc_license_cisuz.jar`
A license file that permits access to the Db2 server.

Modify your CLASSPATH to include these files. If the IBM Data Server Driver for JDBC and SQLJ is installed in `/usr/lpp/db2c10/jdbc`, modify CLASSPATH as follows:

```
export CLASSPATH=/usr/lpp/db2c10_jdbc/classes/db2jcc4.jar:\
/usr/lpp/db2c10/jdbc/classes/db2jcc_javax.jar:\
/usr/lpp/db2c10/jdbc/classes/sqlj4.zip:\
/usr/lpp/db2c10/jdbc/classes/db2jcc_license_cisuz.jar:\
$CLASSPATH
```

If you use Java stored procedures, you need to set additional environment variables in a JAVAENV data set.

Related concepts

"WLM application environment values for Java routines" on page 179
To define the application environment for Java routines to WLM, specify the appropriate values on WLM setup panels.

"Runtime environment for Java routines" on page 180

For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties

The IBM Data Server Driver for JDBC and SQLJ configuration properties let you set property values that have driver-wide scope. Those settings apply across applications and `DataSource` instances. You can change the settings without having to change application source code or `DataSource` characteristics.

Each IBM Data Server Driver for JDBC and SQLJ configuration property setting is of this form:

```
property=value
```

IBM Data Server Driver for JDBC and SQLJ configuration property names are case-sensitive.

You can set configuration properties in the following ways:

- Set the configuration properties as Java system properties. Configuration property values that are set as Java system properties override configuration property values that are set in any other ways.

  For stand-alone Java applications, you can set the configuration properties as Java system properties by specifying -D*property=value* for each configuration property when you execute the java command.

  For Java stored procedures or user-defined functions, you can set the configuration properties by specifying -D*property=value* for each configuration property in a file whose name you specify in the JVMPROPS option. You specify the JVMPROPS options in the ENVAR option of the Language Environment options string. The Language Environment options string is in a data set that is specified by the JAVAENV DD statement in the WLM address space startup procedure.
- Set the configuration properties in a resource whose name you specify in the db2.jcc.propertiesFile Java system property. For example, you can specify an absolute path name for the db2.jcc.propertiesFile value.

  For stand-alone Java applications, you can set the configuration properties by specifying the -Ddb2.jcc.propertiesFile=*path* option when you execute the java command.

  For Java stored procedures or user-defined functions, you can set the configuration properties by specifying the -Ddb2.jcc.propertiesFile=*path/properties-file-name* option in a file whose name you specify in the JVMPROPS option. You specify the JVMPROPS options in the ENVAR option of the Language Environment options string. The Language Environment options string is in a data set that is specified by the JAVAENV DD statement in the WLM address space startup procedure.
- Set the configuration properties in a resource named DB2JccConfiguration.properties. A standard Java resource search is used to find DB2JccConfiguration.properties. The IBM Data Server Driver for JDBC and SQLJ searches for this resource only if you have not set the db2.jcc.propertiesFile Java system property.

  DB2JccConfiguration.properties can be a stand-alone file, or it can be included in a JAR file. If DB2JccConfiguration.properties is a stand-alone file, the contents are automatically converted to Unicode. If you include DB2JccConfiguration.properties in a JAR file, you need to convert the contents to Unicode before you put them in the JAR file.

  If DB2JccConfiguration.properties is a stand-alone file, the path for DB2JccConfiguration.properties must be in the following places:

  – *For stand-alone Java applications:* Include the directory that contains DB2JccConfiguration.properties in the CLASSPATH concatenation.
  – *For Java stored procedures or user-defined functions:* Include the directory that contains DB2JccConfiguration.properties in the CLASSPATH concatenation in the ENVAR option of the Language Environment options string. The Language Environment options string is in a data set that is specified by the JAVAENV DD statement in the WLM address space startup procedure.

If DB2JccConfiguration.properties is in a JAR file, the JAR file must be in the CLASSPATH concatenation.

Example: Putting DB2JccConfiguration.properties in a JAR file: Suppose that your configuration properties are in a file that is in EBCDIC code page 1047. To put the properties file into a JAR file, follow these steps:

1. Rename DB2JccConfiguration.properties to another name, such as EBCDICVersion.properties.
2. Run the iconv shell utility on the z/OS UNIX System Services command line to convert the file contents to Unicode. For example, to convert EBCDICVersion.properties to a Unicode file named DB2JccConfiguration.properties, issue this command:

```
iconv -f ibm-1047 -t utf-8 EBCDICVersion.properties \
  > DB2JccConfiguration.properties
```

3. Execute the jar command to add the Unicode file to the JAR file. In the JAR file, the configuration properties file must be named DB2JccConfiguration.properties. For example:

```
jar -cvf jdbcProperties.jar DB2JccConfiguration.properties
```

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

"IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 288
The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

Enabling the Db2-supplied stored procedures used by the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ requires a set of stored procedures to make certain methods work on Db2 for z/OS.

Before you begin

WLM must be installed on the z/OS system, and a WLM environment must be set up for running the Db2-supplied stored procedures that are required by the IBM Data Server Driver for JDBC and SQLJ.

About this task

The stored procedures that you need to install are:

- SQLCOLPRIVILEGES
- SQLCOLUMNS
- SQLFOREIGNKEYS
- SQLFUNCTIONCOLS
- SQLFUNCTIONS
- SQLGETTYPEINFO
- SQLPRIMARYKEYS
- SQLPROCEDURECOLS
- SQLPROCEDURES
- SQLPSEUDOCOLUMNS
- SQLSPECIALCOLUMNS
- SQLSTATISTICS
- SQLTABLEPRIVILEGES
- SQLTABLES
- SQLUDTS

- SQLCAMESSAGE

Procedure

Follow these steps to install the stored procedures:

1. Set up a WLM environment for running the stored procedures.

   Define WLM application environment DSNWLM_GENERAL to WLM. Application environment DSNWLM_GENERAL and its associated JCL startup procedure, DSNWLMG, are created during Db2 installation. DSNWLM_GENERAL is designed for running the Db2-supplied stored procedures that support JDBC.
2. Define the stored procedures to Db2, and bind the stored procedure packages.

   To perform those tasks, use job DSNTIJRT.

Values for the WLM environment for IBM Data Server Driver for JDBC and SQLJ stored procedures

You need to define an application environment for Db2-supplied stored procedures that support the IBM Data Server Driver for JDBC and SQLJ to WLM.

The following example shows a WLM Definition Menu for an application environment for Db2-supplied stored procedures that support the IBM Data Server Driver for JDBC and SQLJ.

```
  File  Utilities  Notes  Options  Help
------------------------------------------------------------------------
                    Definition Menu     WLM Appl
Command ===> ____________________________________________________________

Definition data set . :  none
Definition name  . . . . DSNWLM_GENERAL
Description . . . . . .  Environment for stored procedures for JDBC
Select one of the
following options. . .   9  1. Policies
                           2. Workloads
                           3. Resource Groups
                           4. Service Classes
                           5. Classification Groups
                           6. Classification Rules
                           7. Report Classes
                           8. Service Coefficients/Options
                           9. Application Environments
                          10. Scheduling Environments
```

Definition name
Specify the name of the WLM application environment that you are setting up for stored procedures. The Definition name value needs to match the APPLENV value in the WLM address space startup procedure.

Description
Specify any value.

Options
Specify 9 (Application Environments).

The following example shows a WLM Create an Application Environment menu with values for the application environment that is used by Db2-supplied stored procedures that support the IBM Data Server Driver for JDBC and SQLJ.

```
  Application-Environment  Notes  Options  Help
------------------------------------------------------------------------------
                     Create an Application Environment
Command ===> ____________________________________________________________

Application Environment Name . : DSNWLM_GENERAL
Description  . . . . . . . . . . Environment for stored procedures for JDBC
Subsystem Type . . . . . . . . . DB2
Procedure Name . . . . . . . . . DSN8WLMG
Start Parameters . . . . . . . . DB2SSN=DB2T,NUMTCB=40,APPLENV=WLMENV
                                 ______________________________________
                                 ______________________________________

Limit on starting server address spaces for a subsystem instance:
1   1.  Managed by WLM
    2.  Single address space per system
    3.  Single address spaces per sysplex
```

Subsystem Type
Specify Db2.

Procedure Name
Specify a name that matches the name of the JCL startup procedure for the stored procedure address spaces that are associated with this application environment.

Start Parameters
If the Db2 subsystem in which the stored procedure runs is not in a sysplex, specify a DB2SSN value that matches the name of that Db2 subsystem. If the same JCL is used for multiple Db2 subsystems, specify DB2SSN=&IWMSSNM. Specify a NUMTCB value between 40 and 60. Specify an APPLENV value that matches the value that you specify in the WLM address space startup procedure and on the CREATE PROCEDURE statements for the stored procedures.

Limit on starting server address spaces for a subsystem instance
Specify 1 (Managed by WLM).

Creation of IBM Data Server Driver for JDBC and SQLJ stored procedures

Db2 provides a JCL job that includes statements that you can use to define the Db2-supplied stored procedures for JDBC and to bind the stored procedure packages.

Job DSNTIJRT is customized by the Db2 installation process to specify WLM environment DSNWLM_GENERAL, which is designed to work with the Db2-supplied stored procedures that support JDBC methods. In general, you run job DSNTIJRT when you install or migration your Db2 subsystem.

DB2Binder utility

The DB2Binder utility binds the Db2 packages that are used at a Db2 for z/OS data server by the IBM Data Server Driver for JDBC and SQLJ, and grants EXECUTE authority on the packages to PUBLIC. Optionally,

the DB2Binder utility can rebind Db2 packages that are not part of the IBM Data Server Driver for JDBC and SQLJ.

DB2Binder syntax



DB2Binder option descriptions

-url

Specifies the data source at which the IBM Data Server Driver for JDBC and SQLJ packages are to be bound. The parts of the `-url` value are:

jdbc:db2:

Indicates that the connection is to a Db2 for z/OS data server.

server

The domain name or IP address of the operating system on which the data server resides.

port

The TCP/IP server port number that is assigned to the data server. The default is 446.

database

The location name for the data server, as defined in the SYSIBM.LOCATIONS catalog table.

property=value

A property and its value for the connection to the Db2 for z/OS data server. You can specify one or more property and value pairs. Each property and value pair, including the last one, must end with a semicolon (;). Do not include spaces or other white space characters anywhere within the list of property and value strings.

For example, if you are building the IBM Data Server Driver for JDBC and SQLJ packages on a Db2 12 for z/OS data server, and you want to specify values for the clientApplcompat and currentPackageSet properties, you can do it in the -url option value like this:

```
-url "jdbc:db2://sys1.svl.ibm.com:5021/STLEC1:clientApplcompat=V12R1M500;currentPackageSet=MYCOLL;"
```

Related information:

“Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products” on page 224

“Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 servers” on page 253

“Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS and IBM Informix” on page 268

“IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS” on page 274

-user

Specifies the user ID under which the packages are to be bound. This user must have BIND authority on the packages.

-action

Specifies the action to perform on the packages.

add

Indicates that a package can be created only if it does not already exist. Add is the default.

replace

Indicates that a package can be created even if a package with the same name already exists. The new package replaces the old package.

rebind

Indicates that the existing package should be rebound. This option does not apply to IBM Data Server Driver for JDBC and SQLJ packages.

If -action rebind and -bindOptions are specified, -generic must also be specified.

drop

Indicates that packages should be dropped:

- For IBM Data Server Driver for JDBC and SQLJ packages, -action drop indicates that some or all IBM Data Server Driver for JDBC and SQLJ packages should be dropped. The number of packages depends on the -size parameter.
- For user packages, -action drop indicates that the specified package should be dropped.

-action drop applies only if the target data server is Db2 for z/OS.

-size
Controls the number of `Statement`, `PreparedStatement`, or `CallableStatement` objects that can be open concurrently, or the number of IBM Data Server Driver for JDBC and SQLJ packages that are dropped.

The meaning of the -size parameter depends on the -action parameter:

- If the value of -action is add or replace, the value of -size is an integer that is used to calculate the number of Db2 packages that the IBM Data Server Driver for JDBC and SQLJ binds. If the value of -size is *integer*, the total number of packages is:

```
number-of-isolation-levels*
number-of-holdability-values*
integer+
number-of-packages-for-static-SQL
= 4*2*integer+1
```

  The default -size value for -action add or -action replace is 3.

  In most cases, the default of 3 is adequate. If your applications throw `SQLExceptions` with -805 SQLCODEs, check that the applications close all unused resources. If they do, increase the -size value.

  If the value of -action is replace, and the value of -size results in fewer packages than already exist, no packages are dropped.
- If the value of -action is drop, the value of -size is the number of packages that are dropped. If -size is not specified, all IBM Data Server Driver for JDBC and SQLJ packages are dropped.
- If the value of -action is rebind, -size is ignored.

-collection
Specifies the collection ID for IBM Data Server Driver for JDBC and SQLJ or user packages. The default is NULLID. DB2Binder translates this value to uppercase.

You can create multiple instances of the IBM Data Server Driver for JDBC and SQLJ packages on a single data server by running `com.ibm.db2.jcc.DB2Binder` multiple times, and specifying a different value for -collection each time. At run time, you select a copy of the IBM Data Server Driver for JDBC and SQLJ by setting the `currentPackageSet` property to a value that matches a -collection value.

-tracelevel
Specifies what to trace while DB2Binder runs. For a list of the valid values, see "DB2TraceManager class" on page 475.

-reopt
Specifies whether data servers determine access paths at run time. This option is not sent to the data server if it is not specified. In that case, the data server determines the reoptimization behavior.

-reopt applies to connections to Db2 for z/OS Version 8 or later, or Db2 on Linux, UNIX, and Windows systems Version 9.1 or later.

none
Specifies that access paths are not determined at run time.

always
Specifies that access paths are determined each time a statement is run.

once
Specifies that Db2 determines and caches the access path for a dynamic statement only once at run time. Db2 uses this access path until the prepared statement is invalidated, or until the statement is removed from the dynamic statement cache and needs to be prepared again.

auto
Specifies that access paths are automatically determined by the data server. auto is valid only for connections to Db2 for z/OS data servers.

-blocking
Specifies the type of row blocking for cursors.

ALL
For cursors that are specified with the FOR READ ONLY clause or are not specified as FOR UPDATE, blocking occurs.

UNAMBIG
For cursors that are specified with the FOR READ ONLY clause, blocking occurs.

Cursors that are not declared with the FOR READ ONLY or FOR UPDATE clause which are not *ambiguous* and are *read-only* will be blocked. *Ambiguous* cursors will not be blocked

NO
Blocking does not occur for any cursor.

For the definition of a read-only cursor and an ambiguous cursor, refer to "DECLARE CURSOR".

-optprofile
Specifies an optimization profile that is used for optimization of data change statements in the packages. This profile is an XML file that must exist on the target server. If -optprofile is not specified, and the CURRENT OPTIMIZATION PROFILE special register is set, the value of CURRENT OPTIMIZATION PROFILE is used. If -optprofile is not specified, and CURRENT OPTIMIZATION PROFILE is not set, no optimization profile is used.

-optprofile is valid only for connections to Db2 on Linux, UNIX, and Windows systems data servers.

-owner
Specifies the authorization ID of the owner of the packages. The default value is set by the data server.

-owner applies only to IBM Data Server Driver for JDBC and SQLJ packages.

-sqlid
Specifies a value to which the CURRENT SQLID special register is set before DB2Binder executes GRANT operations on the IBM Data Server Driver for JDBC and SQLJ packages. If the primary authorization ID does not have a sufficient level of authority to grant privileges on the packages, and the primary authorization ID has an associated secondary authorization ID that has those privileges, set -sqlid to the secondary authorization ID.

-sqlid is valid only for connections to Db2 for z/OS data servers.

-generic
Specifies that DB2Binder rebinds a user package instead of the IBM Data Server Driver for JDBC and SQLJ packages. If -generic is specified, -action rebind and -package must also be specified.

-package
Specifies the name of the package that is to be rebound. This option applies only to user packages. If -package is specified, -action rebind and -generic must also be specified.

-version
Specifies the version ID of the package that is to be rebound. If -version is specified, -action rebind, -package, and -generic must also be specified.

-keepdynamic
Specifies whether the data server keeps already prepared dynamic SQL statements in the dynamic statement cache after the point of commit or rollback so that those prepared statements can be reused. -keepdynamic applies only to connections to Db2 for z/OS.

Possible values are:

no
The data server does not keep already prepared dynamic SQL statements in the dynamic statement cache after the point of commit or rollback.

yes
The data server keeps already prepared dynamic SQL statements in the dynamic statement cache after the point of commit or rollback.

There is no default value for -keepdynamic. If you do not send a value to the data server, the setting at the data server determines whether dynamic statement caching is in effect. Dynamic statement caching occurs only if the EDM dynamic statement cache is enabled on the data server. The CACHEDYN subsystem parameter must be set to YES to enable the dynamic statement cache. Depending on the target server, the prepared statement cache might be preserved across transaction boundaries and not only after commit points.

-release
Specifies when to release data server resources that a program uses. -release applies only to connections to Db2 for z/OS. Possible values are:

deallocate
Specifies that resources are released under either of the following conditions:

- When a program that is locally attached to Db2 for z/OS terminates.
- When all connections are closed from a z/OS application server, such as WebSphere Application Server, that is using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, and the client packages for the applications that are hosted by the application server are bound with RELEASE DEALLOCATE.

-release deallocate is the default for Db2 for z/OS Version 10 and later.

commit
Specifies that resources are released at commit points. -release commit is the default for Db2 for z/OS Version 9 and earlier.

-bindOptions
Specifies a string that is enclosed in quotation marks. The contents of that string are one or more parameter and value pairs that represent options for rebinding a user package. All items in the string are delimited with spaces:

```
"parm1 value1 parm2 value2 … parmn valuen"
```

-bindOptions does not apply to IBM Data Server Driver for JDBC and SQLJ packages that are bound on Db2 on Linux, UNIX, and Windows systems data servers.

You can specify the following -bindOptions values only when you rebind user packages:

bindObjectExistenceRequired
Specifies whether the data server issues an error and does not rebind the package, if all objects or needed privileges do not exist at rebind time. Possible values are:

true
This option corresponds to the SQLERROR(NOPACKAGE) bind option.

false
This option corresponds to the SQLERROR(CONTINUE) bind option.

degreeIOParallelism
Specifies whether to attempt to run static queries using parallel processing to maximize performance. Possible values are:

1
No parallel processing.

This option corresponds to the DEGREE(1) bind option.

-1
Allow parallel processing.

This option corresponds to the DEGREE(ANY) bind option.

packageAuthorizationRules
Determines the values that apply at run time for the following dynamic SQL attributes:

- The authorization ID that is used to check authorization
- The qualifier that is used for unqualified objects
- The source for application programming options that the data server uses to parse and semantically verify dynamic SQL statements
- Whether dynamic SQL statements can include GRANT, REVOKE, ALTER, CREATE, DROP, and RENAME statements

Possible values are:

0
Use run behavior. This is the default.

This option corresponds to the DYNAMICRULES(RUN) bind option.

1
Use bind behavior.

This option corresponds to the DYNAMICRULES(BIND) bind option.

2
When the package is run as or runs under a stored procedure or user-defined function package, the data server processes dynamic SQL statements using invoke behavior. Otherwise, the data server processes dynamic SQL statements using run behavior.

This option corresponds to the DYNAMICRULES(INVOKERUN) bind option.

3
When the package is run as or runs under a stored procedure or user-defined function package, the data server processes dynamic SQL statements using invoke behavior. Otherwise, the data server processes dynamic SQL statements using bind behavior.

This option corresponds to the DYNAMICRULES(INVOKEBIND) bind option.

4
When the package is run as or runs under a stored procedure or user-defined function package, the data server processes dynamic SQL statements using define behavior. Otherwise, the data server processes dynamic SQL statements using run behavior.

This option corresponds to the DYNAMICRULES(DEFINERUN) bind option.

5
When the package is run as or runs under a stored procedure or user-defined function package, the data server processes dynamic SQL statements using define behavior. Otherwise, the data server processes dynamic SQL statements using bind behavior.

This option corresponds to the DYNAMICRULES(DEFINEBIND) bind option.

packageOwnerIdentifier
Specifies the authorization ID of the owner of the packages.

isolationLevel
Specifies how far to isolate an application from the effects of other running applications. Possible values are:

1
Uncommitted read

This option corresponds to the ISOLATION(UR) bind option.

2
Cursor stability

This option corresponds to the ISOLATION(CS) bind option.

3
Read stability

This option corresponds to the ISOLATION(RS) bind option.

4
Repeatable read

This option corresponds to the ISOLATION(RR) bind option.

releasePackageResourcesAtCommit
Specifies when to release resources that a program uses at each commit point. Possible values are:

true
This option corresponds to the RELEASE(COMMIT) bind option.

false
This option corresponds to the RELEASE(DEALLOCATE) bind option.

For connections to Db2 for z/OS data servers, you can also specify any bind package options and their values that are listed in BIND and REBIND options for packages, plans, and services (Db2 Commands).

If -action rebind and -bindOptions are specified, -generic must also be specified.

-verbose
Specifies that the DB2Binder utility displays detailed information about the bind process.

-help
Specifies that the DB2Binder utility describes each of the options that it supports. If any other options are specified with -help, they are ignored.

DB2Binder return codes when the target operating system is not Windows

If the target data source for DB2Binder is not on the Windows operating system, DB2Binder returns one of the following return codes.

Table 109. DB2Binder return codes when the target operating system is not Windows

Return code	Meaning
0	Successful execution.
1	An error occurred during DB2Binder execution.

DB2Binder return codes when the target operating system is Windows

If the target data source for DB2Binder is on the Windows operating system, DB2Binder returns one of the following return codes.

Table 110. DB2Binder return codes when the target operating system is Windows

Return code	Meaning
0	Successful execution.
-100	No bind options were specified.
-101	-url value was not specified.
-102	-user value was not specified.
-103	-password value was not specified.

Table 110. DB2Binder return codes when the target operating system is Windows (continued)

Return code	Meaning
-200	No valid bind options were specified.
-114	The -package option was not specified, but the -generic option was specified.
-201	-url value is invalid.
-204	-action value is invalid.
-205	-blocking value is invalid.
-206	-collection value is invalid.
-207	-dbprotocol value is invalid.
-208	-keepdynamic value is invalid.
-210	-reopt value is invalid.
-211	-size value is invalid.
-212	-tracelevel value is invalid.
-307	-dbprotocol value is not supported by the target data server.
-308	-keepdynamic value is not supported by the target data server.
-310	-reopt value is not supported by the target data server.
-313	-optprofile value is not supported by the target data server.
-401	The `Binder` class was not found.
-402	Connection to the data server failed.
-403	`DatabaseMetaData` retrieval for the data server failed.
-501	No more packages are available in the cluster.
-502	An existing package is not valid.
-503	The bind process returned an error.
-999	An error occurred during processing of an undocumented bind option.

DB2LobTableCreator utility

The DB2LobTableCreator utility creates tables on a Db2 for z/OS database server. Those tables are required by JDBC or SQLJ applications that use LOB locators to access data in DBCLOB or CLOB columns.

DB2LobTableCreator syntax



DB2LobTableCreator option descriptions

-url
Specifies the data source at which DB2LobTableCreator is to run. The variable parts of the `-url` value are:

jdbc:db2:
Indicates that the connection is to a server in the Db2 family.

server
The domain name or IP address of the database server.

port
The TCP/IP server port number that is assigned to the database server. This is an integer between 0 and 65535. The default is 446.

database
A name for the database server.

database is the Db2 location name that is defined during installation. All characters in this value must be uppercase characters. You can determine the location name by executing the following SQL statement on the server:

```
SELECT CURRENT SERVER FROM SYSIBM.SYSDUMMY1;
```

-user
Specifies the user ID under which DB2LobTableCreator is to run. This user must have authority to create tables in the DSNATPDB database.

-password
Specifies the password for the user ID.

-help
Specifies that the DB2LobTableCreator utility describes each of the options that it supports. If any other options are specified with -help, they are ignored.

Verify the installation of the IBM Data Server Driver for JDBC and SQLJ

To verify the installation of the IBM Data Server Driver for JDBC and SQLJ, compile and run any simple JDBC application.

For example, you can compile and run this program to verify your installation:

```
/**
 * File: TestJDBCSelect.java
 *
 * Purpose: Verify IBM Data Server Driver for JDBC and SQLJ installation.
 *          This program uses IBM Data Server Driver for JDBC and SQLJ
 *          type 2 connectivity on Db2 for z/OS.
 *
 * Authorization: This program requires SELECT authority on
 *                DB2 catalog table SYSIBM.SYSTABLES.
 *
 * Flow:
 *   - Load the IBM Data Server Driver for JDBC and SQLJ.
 *   - Get the driver version and display it.
 *   - Establish a connection to the local Db2 for z/OS server.
 *   - Get the DB2 version and display it.
 *   - Execute a query against SYSIBM.SYSTABLES.
 *   - Clean up by closing all open objects.
 */

import java.sql.*;

public class TestJDBCSelect
{
  public static void main(String[] args)
  {
    try
    {
      // Load the driver and get the version
      System.out.println("\nLoading IBM Data Server Driver for JDBC and SQLJ");
```

```
      Class.forName("com.ibm.db2.jcc.DB2Driver");
      System.out.println("  Successful load. Driver version: " +
        com.ibm.db2.jcc.DB2Version.getVersion());

      // Connect to the local Db2 for z/OS server
      System.out.println("\nEstablishing connection to local server");
      Connection conn = DriverManager.getConnection("jdbc:db2:");
      System.out.println("  Successful connect");
      conn.setAutoCommit(false);

      // Use DatabaseMetaData to determine the DB2 version
      System.out.println("\nAcquiring DatabaseMetaData");
      DatabaseMetaData dbmd = conn.getMetaData();
      System.out.println("  DB2 version: " +
                         dbmd.getDatabaseProductVersion());

      // Create a Statement object for executing a query
      System.out.println("\nCreating Statement");
      Statement stmt = conn.createStatement();
      System.out.println("  successful creation of Statement");
      // Execute the query and retrieve the ResultSet object
      String sqlText =
          "SELECT CREATOR, "       +
                "NAME "            +
          "FROM SYSIBM.SYSTABLES " +
          "ORDER BY CREATOR, NAME";
      System.out.println("\nPreparing to execute SELECT");
      ResultSet results = stmt.executeQuery(sqlText);
      System.out.println("  Successful execution of SELECT");

      // Retrieve and display the rows from the ResultSet
      System.out.println("\nPreparing to fetch from ResultSet");
      int recCnt = 0;
      while(results.next())
      {
        String creator = results.getString("CREATOR");
        String name    = results.getString("NAME");
        System.out.println("CREATOR: <" + creator + "> NAME: <" + name + ">");

        recCnt++;
        if(recCnt == 10) break;
      }
      System.out.println("  Successful processing of ResultSet");

      // Close the ResultSet, Statement, and Connection objects
      System.out.println("\nPreparing to close ResultSet");
      results.close();
      System.out.println("  Successful close of ResultSet");

      System.out.println("\nPreparing to close Statement");
      stmt.close();
      System.out.println("  Successful close of Statement");

      System.out.println("\nPreparing to rollback Connection");
      conn.rollback();
      System.out.println("  Successful rollback");

      System.out.println("\nPreparing to close Connection");
      conn.close();
      System.out.println("  Successful close of Connection");
    }
    // Handle errors
    catch(ClassNotFoundException e)
    {
      System.err.println("Unable to load IBM Data Server Driver " +
        "for JDBC and SQLJ, " + e);
    }
    catch(SQLException e)
    {
      System.out.println("SQLException: " + e);
      e.printStackTrace();
    }
  }
}
```

Upgrading the IBM Data Server Driver for JDBC and SQLJ to a new version

Upgrading to a new version of the IBM Data Server Driver for JDBC and SQLJ is similar to installing the IBM Data Server Driver for JDBC and SQLJ for the first time. However, you need to adjust your application programs to work with the new version of the driver.

Before you begin

You should have already completed these steps when you installed the earlier version of the IBM Data Server Driver for JDBC and SQLJ:

1. On Db2 for z/OS, set subsystem parameter DESCSTAT to YES. DESCSTAT corresponds to installation field DESCRIBE FOR STATIC on panel DSNTIPF. This step is necessary for SQLJ support.
2. On Db2 for z/OS, enable the Db2 supplied stored procedures and define the tables that are used by the IBM Data Server Driver for JDBC and SQLJ.

About this task

Procedure

To upgrade the IBM Data Server Driver for JDBC and SQLJ to a new version, follow these steps:

1. In z/OS UNIX System Services, edit your .profile file to customize the environment variable settings. You use this step to set the libraries, paths, and files that the IBM Data Server Driver for JDBC and SQLJ uses.
2. **Optional:** Customize the IBM Data Server Driver for JDBC and SQLJ configuration properties.
3. In z/OS UNIX System Services, run the DB2Binder utility to bind the packages for the IBM Data Server Driver for JDBC and SQLJ.
4. Modify your applications to account for differences between the driver versions.
5. Verify the installation by running a simple JDBC application.

Related concepts

"Verify the installation of the IBM Data Server Driver for JDBC and SQLJ" on page 548
To verify the installation of the IBM Data Server Driver for JDBC and SQLJ, compile and run any simple JDBC application.

"Environment variables for the IBM Data Server Driver for JDBC and SQLJ" on page 534
If you set specific environment variables, the operating system can locate the IBM Data Server Driver for JDBC and SQLJ.

"Runtime environment for Java routines" on page 180
For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

"Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 536
The IBM Data Server Driver for JDBC and SQLJ configuration properties let you set property values that have driver-wide scope. Those settings apply across applications and `DataSource` instances. You can change the settings without having to change application source code or `DataSource` characteristics.

Related tasks

"Enabling the Db2-supplied stored procedures used by the IBM Data Server Driver for JDBC and SQLJ" on page 537
The IBM Data Server Driver for JDBC and SQLJ requires a set of stored procedures to make certain methods work on Db2 for z/OS.

Related reference

"JDBC differences between versions of the IBM Data Server Driver for JDBC and SQLJ" on page 491

Before you can upgrade your JDBC applications from older to newer versions of the IBM Data Server Driver for JDBC and SQLJ, you need to understand the differences between those drivers.

"IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 288
The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

"DB2LobTableCreator utility" on page 547
The DB2LobTableCreator utility creates tables on a Db2 for z/OS database server. Those tables are required by JDBC or SQLJ applications that use LOB locators to access data in DBCLOB or CLOB columns.

"DB2Binder utility" on page 539
The DB2Binder utility binds the Db2 packages that are used at a Db2 for z/OS data server by the IBM Data Server Driver for JDBC and SQLJ, and grants EXECUTE authority on the packages to PUBLIC. Optionally, the DB2Binder utility can rebind Db2 packages that are not part of the IBM Data Server Driver for JDBC and SQLJ.

Installing the z/OS Application Connectivity to Db2 for z/OS feature

z/OS Application Connectivity to Db2 for z/OS is a Db2 for z/OS feature. It allows IBM Data Server Driver for JDBC and SQLJ type 4 connectivity from clients that do not have Db2 for z/OS installed to Db2 for z/OS or Db2 servers on Linux, UNIX, or Windows.

Before you begin

Prerequisites for the IBM Data Server Driver for JDBC and SQLJ:

- Java 2 Technology Edition, V5 or later

  The IBM Data Server Driver for JDBC and SQLJ supports 31-bit or 64-bit Java applications.

  If your applications require a 64-bit JVM, you need to install the IBM 64-bit SDK for z/OS, Java 2 Technology Edition, V5 or later.
- TCP/IP

  TCP/IP is required on the client and all database servers to which you connect.
- Db2 for z/OS distributed data facility (DDF) and TCP/IP support.
- Unicode support for OS/390 and z/OS servers.

About this task

To install the z/OS Application Connectivity to Db2 for z/OS, follow this process. Unless otherwise noted, all steps apply to the z/OS system on which you are installing z/OS Application Connectivity to Db2 for z/OS.

Procedure

To install the z/OS Application Connectivity to Db2 for z/OS feature:

1. Allocate and load the z/OS Application Connectivity to Db2 for z/OS libraries.
2. On all Db2 for z/OS servers to which you plan to connect, set subsystem parameter DESCSTAT to YES. DESCSTAT corresponds to installation field DESCRIBE FOR STATIC on panel DSNTIPF.

   This step is necessary for SQLJ support.
3. In z/OS UNIX System Services, edit your .profile file to customize the environment variable settings. You use this step to set the libraries, paths, and files that the IBM Data Server Driver for JDBC and SQLJ uses.
4. On all Db2 for z/OS servers to which you plan to connect, enable the Db2-supplied stored procedures that are used by the IBM Data Server Driver for JDBC and SQLJ.

5. In z/OS UNIX System Services, run the DB2Binder utility against the z/OS system on which you are installing z/OS Application Connectivity to Db2 for z/OS to bind the packages for the IBM Data Server Driver for JDBC and SQLJ at all Db2 for z/OS servers to which you plan to connect. You need to run DB2Binder once for each server.
6. Verify the installation by running a simple JDBC application.

Related concepts

"Verify the installation of the IBM Data Server Driver for JDBC and SQLJ" on page 548
To verify the installation of the IBM Data Server Driver for JDBC and SQLJ, compile and run any simple JDBC application.

"Environment variables for the IBM Data Server Driver for JDBC and SQLJ" on page 534
If you set specific environment variables, the operating system can locate the IBM Data Server Driver for JDBC and SQLJ.

"Runtime environment for Java routines" on page 180
For Java routines, the startup procedure for the stored procedure address space contains a JAVAENV DD statement. This statement specifies a data set that contains Language Environment runtime options for the routines that run in the stored procedure address space.

"Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 536
The IBM Data Server Driver for JDBC and SQLJ configuration properties let you set property values that have driver-wide scope. Those settings apply across applications and `DataSource` instances. You can change the settings without having to change application source code or `DataSource` characteristics.

Connecting distributed database systems (Db2 Installation and Migration)

Related tasks

"Enabling the Db2-supplied stored procedures used by the IBM Data Server Driver for JDBC and SQLJ" on page 537
The IBM Data Server Driver for JDBC and SQLJ requires a set of stored procedures to make certain methods work on Db2 for z/OS.

Connecting Db2 for z/OS distributed database systems with TCP/IP (Db2 Installation and Migration)

Related reference

"IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 288
The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

"DB2LobTableCreator utility" on page 547
The DB2LobTableCreator utility creates tables on a Db2 for z/OS database server. Those tables are required by JDBC or SQLJ applications that use LOB locators to access data in DBCLOB or CLOB columns.

"DB2Binder utility" on page 539
The DB2Binder utility binds the Db2 packages that are used at a Db2 for z/OS data server by the IBM Data Server Driver for JDBC and SQLJ, and grants EXECUTE authority on the packages to PUBLIC. Optionally, the DB2Binder utility can rebind Db2 packages that are not part of the IBM Data Server Driver for JDBC and SQLJ.

DESCRIBE FOR STATIC field (DESCSTAT subsystem parameter) (Db2 Installation and Migration)

Jobs for loading the z/OS Application Connectivity to Db2 for z/OS libraries

To allocate the HFS or zFS directory structure and to use SMP/E to load the z/OS Application Connectivity to Db2 for z/OS libraries, you need to run jobs that are provided by Db2.

Those jobs are:

DDAALA
Creates the SMP/E consolidate software inventory (CSI) file. DDAALA is required only if the SMP/E target and distribution zones are not created and allocated to the SMP/E global zone.

DDAALB
Creates the z/OS Application Connectivity to Db2 for z/OS target and distribution zones. Also creates DDDEFs for SMP/E data sets. DDAALB is required only if the SMP/E target and distribution zones are not created and allocated to the SMP/E global zone.

DDAALLOC
Creates the z/OS Application Connectivity to Db2 for z/OS target and distribution libraries and defines them in the SMP/E target and distribution zones.

DDADDDEF
Creates DDDEFs for the z/OS Application Connectivity to Db2 for z/OS target and distribution libraries.

DDAISMKD
Invokes the DDAMKDIR EXEC to allocate the HFS or zFS directory structure for the z/OS Application Connectivity to Db2 for z/OS.

DDARECEV
Performs the SMP/E RECEIVE function for the z/OS Application Connectivity to Db2 for z/OS libraries.

DDAAPPLY
Performs the SMP/E APPLY CHECK and APPLY functions for the z/OS Application Connectivity to Db2 for z/OS libraries.

DDAACCEP
Performs the SMP/E ACCEPT CHECK and ACCEPT functions for the z/OS Application Connectivity to Db2 for z/OS libraries.

See *z/OS Application Connectivity to Db2 for z/OS Program Directory* for information on allocating and loading z/OS Application Connectivity to Db2 for z/OS data sets.

Environment variables for the z/OS Application Connectivity to Db2 for z/OS feature

You need to set environment variables so that the operating system can locate the z/OS Application Connectivity to Db2 for z/OS feature.

The environment variables that you must set are:

PATH
Modify PATH to include the directory that contains the shell scripts that invoke IBM Data Server Driver for JDBC and SQLJ program preparation and debugging functions. If z/OS Application Connectivity to Db2 for z/OS is installed in `/usr/lpp/jcct4v3`, modify PATH as follows:

```
export PATH=/usr/lpp/jcct4v3/bin:$PATH
```

CLASSPATH
z/OS Application Connectivity to Db2 for z/OS contains the following class files:

db2jcc4.jar
Include db2jcc4.jar in the CLASSPATH to indicate that you are using the version of the IBM Data Server Driver for JDBC and SQLJ that includes JDBC 4.0 or later functions, and JDBC 3.0 or earlier functions.

sqlj4.zip
Include sqlj4.zip in the CLASSPATH to indicate that you plan to prepare SQLJ applications that include JDBC 4.0 or later functions, and JDBC 3.0 or earlier functions.

db2jcc_license_cisuz.jar
A license file that permits access to Db2 for z/OS servers.

Modify your CLASSPATH to include these files. If z/OS Application Connectivity to Db2 for z/OS is installed in `/usr/lpp/jcct4v3`, modify CLASSPATH as follows:

```
export CLASSPATH=/usr/lpp/jcct4v3/classes/db2jcc4.jar:\
/usr/lpp/jcct4v3/classes/db2jcc_javax.jar:\
/usr/lpp/jcct4v3/classes/sqlj4.zip:\
```

```
/usr/lpp/jcct4v3/classes/db2jcc_license_cisuz.jar:\
$CLASSPATH
```

Chapter 10. Setting the Db2 for z/OS application compatibility for your JDBC and SQLJ applications

You can set the Db2 for z/OS application compatibility for Java applications by specifying a bind option for static applications, or a special register for dynamic applications.

About this task

Starting with Db2 for z/OS Version 11, you can choose whether to use SQL behavior that is available in new-function mode of the new Db2 for z/OS version, or continue to use SQL behavior from the previous version. This feature is called application compatibility. You can set the application compatibility level for an entire Db2 for z/OS subsystem, or for individual application packages.

The IBM Data Server Driver for JDBC and SQLJ provides several ways to set the application static SQLJ applications or for dynamic JDBC or SQLJ applications.

Procedure

To set the application compatibility for Java applications, follow one of these procedures.

- For JDBC or dynamic SQLJ applications, set the CURRENT APPLICATION COMPATIBILITY special register.

  You can do that using the `DB2DataSource.setSpecialRegisters` method, or by specifying the specialRegisters option in the connection URL.
- For static SQLJ applications, specify the APPLCOMPAT bind option in the -bindoptions string when you bind the application packages using the db2sqljcustomize or db2sqljbind command. You can also specify the APPLCOMPAT rebind option using the DB2Binder utility.

Examples

Example: In a JDBC application that uses the `DriverManager` interface, set the application compatibility to V11R1 in the connection URL.

```
String url =
     "jdbc:db2://sysmvs1.svl.ibm.com:5021/STLEC1" +
     ":user=dbadm;password=dbadm;" +
     "specialRegisters=CURRENT APPLICATION COMPATIBILITY='V11R1'" + ";";
    Connection con =
       java.sql.DriverManager.getConnection(url);
```

Example: In a JDBC application that uses the `DataSource` interface, set the application compatibility to V10R1 using the `setSpecialRegisters` method.

```
DB2DataSource ds = new DB2DataSource();
…
Properties prop = new Properties();
prop.add("CURRENT APPLICATION COMPATIBILITY","V10R1");
…
ds.setSpecialRegisters(prop);
```

Example: Customize and bind the package for serialized profile EzSqlj_SJProfile0.ser so that the application is compatible with Db2 for z/OS Version 10.

```
db2sqljcustomize -user myid -password mypw
     -url jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1
     -bindoptions "APPLCOMPAT(V10R1)" EzSqlj_SJProfile0.ser
```

© Copyright IBM Corp. 1998, 2017

Example: Rebind packages EZSQLJ01, EZSQLJ02, EZSQLJ03, and EXSQLJ04 for serialized profile EzSqlj_SJProfile0.ser so that the application is compatible with Db2 for z/OS Version 11.

```
java com.ibm.db2.jcc.DB2Binder
     -url jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1 -user myid -password mypw
     -bindoptions "APPLCOMPAT V11R1" -generic -action rebind -collection mycoll
     -package EZSQLJ01
java com.ibm.db2.jcc.DB2Binder
     -url jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1 -user myid -password mypw
     -bindoptions "APPLCOMPAT V11R1" -generic -action rebind -collection mycoll
     -package EZSQLJ02
java com.ibm.db2.jcc.DB2Binder
     -url jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1 -user myid -password mypw
     -bindoptions "APPLCOMPAT V11R1" -generic -action rebind -collection mycoll
     -package EZSQLJ03
java com.ibm.db2.jcc.DB2Binder
     -url jdbc:db2://sysmvs1.stl.ibm.com:5021/STLEC1 -user myid -password mypw
     -bindoptions "APPLCOMPAT V11R1" -generic -action rebind -collection mycoll
     -package EZSQLJ04
```

Related concepts

Application compatibility levels in Db2 (Db2 Application programming and SQL)

Chapter 11. Installing, updating, or upgrading the IBM Data Server Driver for JDBC and SQLJ on Db2 on Linux, UNIX, and Windows systems

After you install, update, or upgrade the IBM Data Server Driver for JDBC and SQLJ, you can prepare and run JDBC or SQLJ applications.

Before you begin

Before you install the IBM Data Server Driver for JDBC and SQLJ, you need the following software.

- An SDK for Java

  For the most up-to-date SDK for Java requirements for Db2 database products, see the System requirements for IBM DB2 for Linux, UNIX, and Windows and System requirements for IBM DB2 Connect IBM Support pages. Click on the Software requirements link for the appropriate Db2 or Db2 Connect level to see a page that contains the Java requirements.
- JVM native threads support

  Any JVMs that run Java applications that access Db2 databases must include native threads support. You can specify native threads as the default thread support for some JVMs by setting the THREADS_FLAG environment variable to "native". Refer to the documentation for your Java environment for instructions on making native threads the default on your system.

About this task

Restriction: If you install the IBM Data Server Driver for JDBC and SQLJ on a Windows 64-bit operating system, you cannot use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to connect to a Db2 on Linux, UNIX, and Windows systems instance from a 32-bit Java application.

Follow these steps to install the IBM Data Server Driver for JDBC and SQLJ.

Procedure

1. During the Db2 on Linux, UNIX, and Windows systems installation process, select `Java support` on UNIX or Linux, or `JDBC support` on Windows.

   These selections are defaults. If you have already installed Db2 on Linux, UNIX, and Windows systems without JDBC support, you can run the installation process in `Custom` mode to add JDBC support.

   Selection of `Java support` or `JDBC support` causes the installation process to perform the following actions:

   a. Installs the IBM Data Server Driver for JDBC and SQLJ class files.

      The files are placed in the sqllib\java directory for Windows systems, or the sqllib/java directory for UNIX or Linux systems.

      The file names are:

      db2jcc4.jar
      db2jcc4.jar includes JDBC 4.0 or later functions, and JDBC 3.0 or earlier functions.

      sqlj4.zip

      sqlj4.zip supports SQLJ applications that include JDBC 4.0 or later functions, and JDBC 3.0 or earlier functions.

© Copyright IBM Corp. 1998, 2017

Important: You need to modify the CLASSPATH variable to include the db2jcc4.jar file and the sqlj4.zip file. If the CLASSPATH variable already includes the unsupported db2jcc.jar or sqlj.zip files, remove them.

You also need to make this change in every Db2 command line window that you open.

b. If IBM Data Server Driver for JDBC and SQLJ client license file exists, the installation process installs them and modifies the CLASSPATH variable to include them.

The files are placed in the sqllib\java directory for Windows systems, or the sqllib/java directory for UNIX or Linux systems.

If you downloaded the db2jcc_license_cisuz.jar file from Passport Advantage®, you need to update the CLASSPATH variable to include the path to the license file and the license file name. For example:

- For Windows systems: Suppose that the license file is in relative path sqllib\java. Update the CLASSPATH variable as follows:

```
set CLASSPATH=path to sqllib\java\db2jcc_license_cisuz.jar:%CLASSPATH%
```

- For Linux or UNIX systems: Suppose that the license file is in relative path sqllib/java. Update the CLASSPATH variable as follows:

```
export CLASSPATH=path to sqllib/java/db2jcc_license_cisuz.jar;$CLASSPATH
```

The file names are:

Table 111. IBM Data Server Driver for JDBC and SQLJ license files

License file	Server to which license file permits a connection	Product that includes license file
db2jcc_license_cisuz.jar	Db2 for z/OS Db2 for IBM i	All Db2 Connect products

Client license files are not required for connections to Db2 on Linux, UNIX, and Windows systems, Cloudscape, or IBM Informix databases from the IBM Data Server Driver for JDBC and SQLJ version 3.50 or later.

c. Installs IBM Data Server Driver for JDBC and SQLJ native libraries for support of IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

The files are placed in the sqllib\bin directory for Windows systems, or the sqllib/lib directory for UNIX or Linux systems.

The file names are:

libdb2jcct2.so
For AIX® and Linux

db2jcct2.dll
For Windows

2. After you have completed step "1" on page 557, you can download and install the latest versions of the IBM Data Server Driver for JDBC and SQLJ class files by following these steps.

a. Go to the Download Fix Packs by version for IBM Data Server Client Packages page.

b. From the **IBM Data Server Client Packages Fix Packs by version** table, click the link for the desired version and fix pack level.

c. In the **IBM Data Server Client Packages** page, look in the table for the row with IBM Data Server Driver for JDBC and SQLJ in the **Product Fix Pack description** column and the operating system that you need in the **Download** column. Click the link.

d. In the **Select Fixes** page, select the box for the desired fix pack. Click Continue.

e. If the **Log in to IBM** page appears, enter your IBM ID and password.

f. If the **Download options** page appears, select the download options that are appropriate for you. Click **Continue**.

g. In the **Download files** page, click **Download now**.

h. After the download completes, extract the fix pack files into a directory. Then extract the `db2_db2driver_for_jdbc_sqlj.zip` file into an empty directory.

The zip file contains the following files:

- `db2jcc4.jar`
- `sqlj4.zip`

i. Copy the files to the locations that are specified in step "1.a" on page 557 above.

j. Modify the CLASSPATH variable to include the IBM Data Server Driver for JDBC and SQLJ class files. If the CLASSPATH variable already includes the unsupported db2jcc.jar or sqlj.zip files, remove them.

3. Customize the driver-wide configuration properties, if any of the defaults are inappropriate.
4. Configure TCP/IP.

Servers must be configured for TCP/IP communication in the following cases:

- JDBC or SQLJ applications that use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.
- JDBC or SQLJ applications that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, and specify *server* and *port* in the connection URL.

Ensure that the TCP/IP listener is running. To activate the TCP/IP listener:

a) Set the environment variable DB2COMM to TCPIP:

```
db2set DB2COMM=TCPIP
```

b) Update the database manager configuration file with the TCP/IP service name as specified in the services file:

```
db2 update dbm cfg using SVCENAME TCP/IP-service-name
```

The port number used for applets and SQLJ programs needs to be the same as the TCP/IP SVCENAME number used in the database manager configuration file.

c) Execute the db2stop and db2start commands for the service name setting to take effect.

5. On Db2 on Linux, UNIX, and Windows systems servers on which you plan to run Java stored procedures or user-defined functions, update the database manager configuration to include the path where the SDK for Java is located.

You can do this by entering commands similar to these on the server command line:

- *For database systems on UNIX or Linux:*

```
db2 update dbm cfg using JDK_PATH /home/db2inst/jdk15
```

/home/db2inst/jdk15 is the path where the SDK for Java is installed.

- *For database systems on Windows:*

```
db2 update dbm cfg using JDK_PATH c:\Program Files\jdk15
```

c:\Program Files\jdk15 is the path where the SDK for Java is installed.

To verify the correct value for the JDK_PATH field in the Db2 database manager configuration, enter the following command on the database server:

```
db2 get dbm cfg
```

You might want to redirect the output to a file for easier viewing. The JDK_PATH field appears near the beginning of the output.

6. If you plan to call SQL procedures that are on Db2 on Linux, UNIX, and Windows systems servers from Java programs, and the date and time format that is associated with the territory code of the database servers is **not** the USA format, take the following actions:
   a) Set the DB2_SQLROUTINE_PREPOPTS registry variable on the database servers to indicate that the default datetime format is ISO:

   ```
   db2set DB2_SQLROUTINE_PREPOPTS="DATETIME ISO"
   ```

   b) Redefine any existing SQL procedures that you plan to call from Java programs.

   These steps are necessary to ensure that the calling application receives date and time values correctly.
7. If you plan to access Db2 for z/OS data servers with your Java applications, follow the instructions in "Special setup for accessing Db2 for z/OS servers from Java programs" in *Developing Java Applications*.

Special setup for accessing Db2 for z/OS servers from Java programs

If you plan to write JDBC or SQLJ applications that access Db2 for z/OS database servers, your IBM Data Server Driver for JDBC and SQLJ installation process requires additional steps.

Procedure

Follow these steps to allow connectivity to Db2 for z/OS servers:

1. Run the com.ibm.db2.jcc.DB2Binder utility to bind the Db2 packages that are used at the server by the IBM Data Server Driver for JDBC and SQLJ.
2. On Db2 for z/OS database servers, customize and run job DSNTIJRT.

   DSNTIJRT is located in data set *prefix*.SDSNSAMP. It performs the following functions to support the IBM Data Server Driver for JDBC and SQLJ:

   - Creates the following stored procedures to support `DatabaseMetaData` methods, tracing, and error message formatting.
     - SYSIBM.SQLCAMESSAGE
     - SYSIBM.SQLCOLPRIVILEGES
     - SYSIBM.SQLCOLUMNS
     - SYSIBM.SQLFOREIGNKEYS
     - SYSIBM.SQLFUNCTIONCOLS
     - SYSIBM.SQLFUNCTIONS
     - SYSIBM.SQLGETTYPEINFO
     - SYSIBM.SQLPRIMARYKEYS
     - SYSIBM.SQLPROCEDURECOLS
     - SYSIBM.SQLPROCEDURES
     - SYSIBM.SQLPSEUDOCOLUMNS
     - SYSIBM.SQLSPECIALCOLUMNS
     - SYSIBM.SQLSTATISTICS
     - SYSIBM.SQLTABLEPRIVILEGES
     - SYSIBM.SQLTABLES
     - SYSIBM.SQLUDTS

- Creates the following tables, which are used by the stored procedures for `DatabaseMetaData` support:
  - SYSIBM.SQTCOLPRIVILEGES
  - SYSIBM.SQTCOLUMNS
  - SYSIBM.SQTFOREIGNKEYS
  - SYSIBM.SQTPRIMARYKEYS
  - SYSIBM.SQTPROCEDURECOLS
  - SYSIBM.SQTPROCEDURES
  - SYSIBM.SQTSPECIALCOLUMNS
  - SYSIBM.SQTSTATISTICS
  - SYSIBM.SQTTABLEPRIVILEGES
  - SYSIBM.SQTTABLES
  - SYSIBM.SQLTABLETYPES
  - SYSIBM.SQLTYPEINFO
  - SYSIBM.UINDEXES
  - SYSIBM.SQTUDTS

Chapter 12. Security under the IBM Data Server Driver for JDBC and SQLJ

When you use the IBM Data Server Driver for JDBC and SQLJ, you choose a security mechanism by specifying a value for the securityMechanism `Connection` or `DataSource` property, or the db2.jcc.securityMechanism global configuration property.

Important: The DATA_ENCRYPT authentication type is deprecated and might be removed in a future release. To encrypt data in-transit between clients and Db2 on Linux, UNIX, and Windows systems databases, we recommend that you use the Db2 on Linux, UNIX, and Windows systems database system support of Secure Sockets Layer (SSL).

You can set the securityMechanism property in one of the following ways:

- If you use the `DriverManager` interface, set `securityMechanism` in a `java.util.Properties` object before you invoke the form of the `getConnection` method that includes the `java.util.Properties` parameter.
- If you use the `DataSource` interface, and you are creating and deploying your own `DataSource` objects, invoke the `DataSource.setSecurityMechanism` method after you create a `DataSource` object.

You can determine the security mechanism that is in effect for a connection by calling the `DB2Connection.getDB2SecurityMechanism` method.

The following table lists the security mechanisms that the IBM Data Server Driver for JDBC and SQLJ supports, and the data sources that support those security mechanisms.

Table 112. Data server support for IBM Data Server Driver for JDBC and SQLJ security mechanisms

Security mechanism	Supported by Db2 on Linux, UNIX, and Windows systems	Supported by Db2 for z/OS	Supported by IBM Informix	Supported by Db2 for IBM i
User ID and password	Yes	Yes	Yes	Yes
User ID only	Yes	Yes	Yes	Yes
User ID and encrypted password"1" on page 564	Yes	Yes	Yes	Yes"3" on page 564
Encrypted user ID"1" on page 564	Yes	Yes	No	No
Encrypted user ID and encrypted password"1" on page 564	Yes	Yes	Yes	Yes"3" on page 564
Encrypted user ID and encrypted security-sensitive data"1" on page 564	No	Yes	No	No
Encrypted user ID, encrypted password, and encrypted security-sensitive data"1" on page 564	Yes	Yes	No	No
Kerberos"2" on page 564	Yes	Yes	No	Yes
Plugin"2" on page 564	Yes	No	No	No

© Copyright IBM Corp. 1998, 2017

Table 112. Data server support for IBM Data Server Driver for JDBC and SQLJ security mechanisms (continued)

Security mechanism	Supported by Db2 on Linux, UNIX, and Windows systems	Supported by Db2 for z/OS	Supported by IBM Informix	Supported by Db2 for IBM i
Certificate authentication"2" on page 564	No	Yes	No	No
Token authentication	Yes	No	No	No

Note:

1. These security mechanisms use DRDA encryption. DRDA encryption is not intended to provide confidentiality and integrity of passwords or data over a network that is not secure, such as the Internet. DRDA encryption uses an anonymous key exchange, Diffie-Hellman, which does not provide authentication of the server or the client. DRDA encryption is vulnerable to man-in-the-middle attacks.
2. Available for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.
3. The version of the data source must be Db2 for IBM i V6R1 or later.

The following table lists the security mechanisms that the IBM Data Server Driver for JDBC and SQLJ supports, and the value that you need to specify for the `securityMechanism` property to specify each security mechanism.

Important:

Starting with version 4.33 of the IBM Data Server Driver for JDBC and SQLJ:

- The default security mechanism is `ENCRYPTED_USER_AND_PASSWORD_SECURITY`. If the data server does not support `ENCRYPTED_USER_AND_PASSWORD_SECURITY`, but supports `CLEAR_TEXT_PASSWORD_SECURITY`, the driver changes the security mechanism to `CLEAR_TEXT_PASSWORD_SECURITY` and attempts to connect to the data server. The connection retry using CLEAR_TEXT_PASSWORD_SECURITY might cause a slight performance impact. Any other mismatch in security mechanism support between the requester and the data server results in an error.
- A connection to a Db2 for z/OS subsystem or data sharing group that uses the default security mechanism of `ENCRYPTED_USER_AND_PASSWORD_SECURITY` and AES encryption is successful only if the z/OS Integrated Cryptographic Service Facility (ICSF) is enabled on the z/OS system where each subsystem or data sharing member is installed. ICSF is required for decrypting the user ID and password. If ICSF is not installed, you need to set the security mechanism to `CLEAR_TEXT_PASSWORD_SECURITY`.

Before version 4.33 of the IBM Data Server Driver for JDBC and SQLJ, the default security mechanism is `CLEAR_TEXT_PASSWORD_SECURITY`. If the data server does not support `CLEAR_TEXT_PASSWORD_SECURITY`, but supports `ENCRYPTED_USER_AND_PASSWORD_SECURITY`, the driver changes the security mechanism to `ENCRYPTED_USER_AND_PASSWORD_SECURITY` and attempts to connect to the data server. Any other mismatch in security mechanism support between the requester and the data server results in an error.

Table 113. Security mechanisms supported by the IBM Data Server Driver for JDBC and SQLJ

Security mechanism	**securityMechanism property value**
User ID and password	`DB2BaseDataSource.CLEAR_TEXT_PASSWORD_SECURITY` (3)
User ID only	`DB2BaseDataSource.USER_ONLY_SECURITY` (4)
User ID and encrypted password"1" on page 565	`DB2BaseDataSource.ENCRYPTED_PASSWORD_SECURITY` (7)
Encrypted user ID"1" on page 565	`DB2BaseDataSource.ENCRYPTED_USER_ONLY_SECURITY` (16)

Table 113. Security mechanisms supported by the IBM Data Server Driver for JDBC and SQLJ (continued)

Security mechanism	securityMechanism property value
Encrypted user ID and encrypted password"1" on page 565	DB2BaseDataSource.ENCRYPTED_USER_AND_PASSWORD_SECURITY (9)
Encrypted user ID and encrypted security-sensitive data"1" on page 565	DB2BaseDataSource.ENCRYPTED_USER_AND_DATA_SECURITY (12)
Encrypted user ID, encrypted password, and encrypted security-sensitive data"1" on page 565	DB2BaseDataSource.ENCRYPTED_USER_PASSWORD_AND_DATA_SECURITY (13)
Kerberos	DB2BaseDataSource.KERBEROS_SECURITY (11)
Plugin	DB2BaseDataSource.PLUGIN_SECURITY (15)
Certificate authentication	DB2BaseDataSource.TLS_CLIENT_CERTIFICATE_SECURITY (18)
Token authentication	DB2BaseDataSource.TOKEN_SECURITY (19)

Note:

1. DRDA encryption is not intended to provide confidentiality and integrity of passwords or data over a network that is not secure, such as the Internet. DRDA encryption uses an anonymous key exchange, Diffie-Hellman, which does not provide authentication of the server or the client. DRDA encryption is vulnerable to man-in-the-middle attacks.

Related concepts

"User ID and password security under the IBM Data Server Driver for JDBC and SQLJ" on page 565
With the IBM Data Server Driver for JDBC and SQLJ, one of the available security methods is user ID and password security.

"User ID-only security under the IBM Data Server Driver for JDBC and SQLJ" on page 568
With the IBM Data Server Driver for JDBC and SQLJ, one of the available security methods is user-ID only security.

"Kerberos security under the IBM Data Server Driver for JDBC and SQLJ" on page 571
JDBC support for Kerberos security is available for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

"Encrypted password, user ID, or data security under the IBM Data Server Driver for JDBC and SQLJ" on page 569
IBM Data Server Driver for JDBC and SQLJ supports encryption of user IDs, passwords, or data when Java applications access data servers.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

User ID and password security under the IBM Data Server Driver for JDBC and SQLJ

With the IBM Data Server Driver for JDBC and SQLJ, one of the available security methods is user ID and password security.

To specify user ID and password security for a JDBC connection, use one of the following techniques.

For the `DriverManager` interface: You can specify the user ID and password directly in the `DriverManager.getConnection` invocation. For example:

```
import java.sql.*;         // JDBC base
…
String id = "dbadm";       // Set user ID
String pw = "dbadm";       // Set password
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                           // Set URL for the data source

Connection con = DriverManager.getConnection(url, id, pw);
                           // Create connection
```

Another method is to set the user ID and password directly in the URL string. For example:

```
import java.sql.*;         // JDBC base
…
String url =
  "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose:user=dbadm;password=dbadm;";

                           // Set URL for the data source
Connection con = DriverManager.getConnection(url);
                           // Create connection
```

Alternatively, you can set the user ID and password by setting the `user` and `password` properties in a `Properties` object, and then invoking the form of the `getConnection` method that includes the `Properties` object as a parameter. Optionally, you can set the `securityMechanism` property to indicate that you are using user ID and password security. For example:

```
import java.sql.*;                         // JDBC base
import com.ibm.db2.jcc.*;                  // IBM Data Server Driver for JDBC
                                           // and SQLJ implementation of JDBC
…
Properties properties = new java.util.Properties();
                                           // Create Properties object
properties.put("user", "dbadm");           // Set user ID for the connection
properties.put("password", "dbadm");       // Set password for the connection
properties.put("securityMechanism",
  new String("" + com.ibm.db2.jcc.DB2BaseDataSource.CLEAR_TEXT_PASSWORD_SECURITY +
  ""));
                                           // Set security mechanism to
                                           // user ID and password
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                                           // Set URL for the data source
Connection con = DriverManager.getConnection(url, properties);
                                           // Create connection
```

For the `DataSource` interface: you can specify the user ID and password directly in the `DataSource.getConnection` invocation. For example:

```
import java.sql.*;                         // JDBC base
import com.ibm.db2.jcc.*;                  // IBM Data Server Driver for JDBC
                                           // and SQLJ implementation of JDBC
…
Context ctx=new InitialContext();          // Create context for JNDI
DataSource ds=(DataSource)ctx.lookup("jdbc/sampledb");
                                           // Get DataSource object
String id = "dbadm";                       // Set user ID
String pw = "dbadm";                       // Set password
Connection con = ds.getConnection(id, pw);
                                           // Create connection
```

Alternatively, if you create and deploy the `DataSource` object, you can set the user ID and password by invoking the `DataSource.setUser` and `DataSource.setPassword` methods after you create the `DataSource` object. Optionally, you can invoke the `DataSource.setSecurityMechanism` method property to indicate that you are using user ID and password security. For example:

```
…
com.ibm.db2.jcc.DB2SimpleDataSource ds =       // Create DB2SimpleDataSource object
  new com.ibm.db2.jcc.DB2SimpleDataSource();
ds.setDriverType(4);                           // Set driver type
ds.setDatabaseName("san_jose");                // Set location
ds.setServerName("mvs1.sj.ibm.com");           // Set server name
```

```
ds.setPortNumber(5021);                          // Set port number
ds.setUser("dbadm");                             // Set user ID
ds.setPassword("dbadm");                         // Set password
ds.setSecurityMechanism(
  com.ibm.db2.jcc.DB2BaseDataSource.CLEAR_TEXT_PASSWORD_SECURITY);
                                                 // Set security mechanism to
                                                 // user ID and password
```

IBM Data Server Driver for JDBC and SQLJ type 2 connectivity with no user ID or password: For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, if you use user ID and password security, but you do not specify a user ID and password, the database system uses the external security environment, such as the RACF security environment, that was previously established for the user. For a CICS connection, you cannot specify a user ID or password.

Valid characters in passwords: All characters in the ASCII range X'20' (decimal 32) through X'7E' (decimal 126) are valid in passwords, except for the following characters:

- X'20' (space) at the end of a password. The IBM Data Server Driver for JDBC and SQLJ strips space characters at the end of a password.
- X'3B' (semicolon)
- Any characters that cannot be converted to EBCDIC characters, if passwords in plain text are sent to a data server.

RACF password phrase security: If you are connecting to a Db2 for z/OS that is configured for RACF protection, and the RACF version supports RACF password phrases, you can supply a RACF password phrase for the password property value, instead of a simple password. A password phrase must conform to the following rules:

- A password phrase is a character string that can consist of mixed-case letters, numbers, and special characters, including blanks.
- The length of the password phrase can be 9 to 100 characters, or 14 to 100 characters.

  Password phrases of between 9 and 13 characters are allowed when the new-password-phrase exit (ICHPWX11) is installed on the z/OS system, and the exit allows password phrases of fewer than 14 characters.
- A password phrase must not contain the user ID, as sequential uppercase or sequential lowercase characters.
- A password phrase must contain at least two alphabetic characters (A through Z or a through z).
- A password phrase must contain at least two non-alphabetic characters (numerics, punctuation, or special characters).
- A password phrase must not contain more than two consecutive characters that are identical.
- If a single quotation mark (') is part of the password phrase, the single quotation mark must be represented as two consecutive single quotation marks ('').

The following example uses a password phrase for a connection:

```
import java.sql.*;                           // JDBC base
import com.ibm.db2.jcc.*;                    // IBM Data Server Driver for JDBC
                                             // and SQLJ implementation of JDBC
…
Properties properties = new java.util.Properties();
                                             // Create Properties object
properties.put("user", "dbadm");             // Set user ID for the connection
properties.put("password", "a*b!c@ D12345 678");
                                             // Set password phrase for the connection
properties.put("securityMechanism",
  new String("" + com.ibm.db2.jcc.DB2BaseDataSource.CLEAR_TEXT_PASSWORD_SECURITY +
  ""));
                                             // Set security mechanism to
                                             // user ID and password
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                                             // Set URL for the data source
Connection con = DriverManager.getConnection(url, properties);
                                             // Create connection
```

Related tasks

"Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ" on page 13
A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

"Creating and deploying DataSource objects" on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

"Connecting to a data source using the DataSource interface" on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

User ID-only security under the IBM Data Server Driver for JDBC and SQLJ

With the IBM Data Server Driver for JDBC and SQLJ, one of the available security methods is user-ID only security.

To specify user ID security for a JDBC connection, use one of the following techniques.

For the `DriverManager` interface: Set the user ID and security mechanism by setting the `user` and `securityMechanism` properties in a `Properties` object, and then invoking the form of the `getConnection` method that includes the `Properties` object as a parameter. For example:

```
import java.sql.*;                      // JDBC base
import com.ibm.db2.jcc.*;               // IBM Data Server Driver
                                        // for JDBC and SQLJ
                                        // implementation of JDBC
…
Properties properties = new Properties();
                                        // Create a Properties object
properties.put("user", "db2adm");       // Set user ID for the connection
properties.put("securityMechanism",
  new String("" + com.ibm.db2.jcc.DB2BaseDataSource.USER_ONLY_SECURITY + ""));
                                        // Set security mechanism to
                                        // user ID only
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                                        // Set URL for the data source
Connection con = DriverManager.getConnection(url, properties);
                                        // Create the connection
```

For the `DataSource` interface: If you create and deploy the `DataSource` object, you can set the user ID and security mechanism by invoking the `DataSource.setUser` and `DataSource.setSecurityMechanism` methods after you create the `DataSource` object. For example:

```
import java.sql.*;                      // JDBC base
import com.ibm.db2.jcc.*;               // IBM Data Server Driver
                                        // for JDBC and SQLJ
                                        // implementation of JDBC
…
com.ibm.db2.jcc.DB2SimpleDataSource db2ds =
  new com.ibm.db2.jcc.DB2SimpleDataSource();
                                        // Create DB2SimpleDataSource object
db2ds.setDriverType(4);                 // Set the driver type
db2ds.setDatabaseName("san_jose");      // Set the location
db2ds.setServerName("mvs1.sj.ibm.com");
                                        // Set the server name
db2ds.setPortNumber(5021);              // Set the port number
db2ds.setUser("db2adm");                // Set the user ID
db2ds.setSecurityMechanism(
  com.ibm.db2.jcc.DB2BaseDataSource.USER_ONLY_SECURITY);
```

```
                                        // Set security mechanism to
                                        // user ID only
```

Related tasks

"Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ" on page 13
A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

"Creating and deploying DataSource objects" on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

"Connecting to a data source using the DataSource interface" on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

Encrypted password, user ID, or data security under the IBM Data Server Driver for JDBC and SQLJ

IBM Data Server Driver for JDBC and SQLJ supports encryption of user IDs, passwords, or data when Java applications access data servers.

Those security mechanisms use DRDA encryption. DRDA encryption is not intended to provide confidentiality and integrity of passwords or data over a network that is not secure, such as the Internet. DRDA encryption uses an anonymous key exchange, Diffie-Hellman, which does not provide authentication of the server or the client. DRDA encryption is vulnerable to man-in-the-middle attacks.

The IBM Data Server Driver for JDBC and SQLJ supports 56-bit DES (weak) encryption or 256-bit AES (strong) encryption. AES encryption is available with IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only. You set the encryptionAlgorithm driver property to choose between 56-bit DES encryption (encryptionAlgorithm value of 1) and 256-bit AES encryption (encryptionAlgorithm value of 2). 256-bit AES encryption is used for a connection only if the database server supports it and is configured to use it.

If you use encrypted password security, encrypted user ID security, or encrypted user ID and encrypted password security from a Db2 for z/OS client, the Java Cryptography Extension, IBMJCE for z/OS needs to be enabled on the client. The Java Cryptography Extension is part of the IBM Developer Kit for z/OS, Java 2 Technology Edition. For information on how to enable IBMJCE, go to this URL on the web: http://www.ibm.com/servers/eserver/zseries/software/java/j5jce.html

For AES encryption, you need to get the unrestricted policy file for JCE. It is available at the following URL:

```
https://www.ibm.com/marketing/iwm/iwm/web/preLogin.do?source=jcesdk
```

Connections to Db2 for IBM i V6R1 or later servers can use encrypted password security or encrypted user ID and encrypted password security. For encrypted password security or encrypted user ID and encrypted password security, the IBM Java Cryptography Extension (ibmjceprovidere.jar) must be installed on your client. The IBM JCE is part of the IBM SDK for Java, Version 1.4.2 or later.

You can also use encrypted security-sensitive data in addition to encrypted user ID security or encrypted user ID and encrypted password security. You specify encryption of security-sensitive data through the `ENCRYPTED_USER_AND_DATA_SECURITY` or `ENCRYPTED_USER_PASSWORD_AND_DATA_SECURITY` `securityMechanism` value. `ENCRYPTED_USER_AND_DATA_SECURITY` is valid for connections to Db2 for z/OS servers only.

Db2 for z/OS or Db2 on Linux, UNIX, and Windows systems database servers encrypt the following data when you specify encryption of security-sensitive data:

- SQL statements that are being prepared, executed, or bound into a package
- Input and output parameter information
- Result sets
- LOB data
- XML data
- Results of describe operations

Before you can use encrypted security-sensitive data, the z/OS Integrated Cryptographic Services Facility needs to be installed and enabled on the z/OS operating system.

To specify encrypted user ID or encrypted password security for a JDBC connection, use one of the following techniques.

For the `DriverManager` interface: Set the user ID, password, and security mechanism by setting the `user`, `password`, and `securityMechanism` properties in a `Properties` object, and then invoking the form of the `getConnection` method that includes the `Properties` object as a parameter. For example, use code like this to set the encrypted user ID and encrypted password security mechanism, with AES encryption:

```
import java.sql.*;                          // JDBC base
import com.ibm.db2.jcc.*;                   // IBM Data Server Driver for JDBC
                                            // and SQLJ implementation of JDBC
…
Properties properties = new Properties(); // Create a Properties object
properties.put("user", "dbadm");            // Set user ID for the connection
properties.put("password", "dbadm");        // Set password for the connection
properties.put("securityMechanism",
  new String("" +
  com.ibm.db2.jcc.DB2BaseDataSource.ENCRYPTED_USER_AND_PASSWORD_SECURITY +
  ""));
                                            // Set security mechanism to
                                            // user ID and encrypted password
properties.put("encryptionAlgorithm", "2");
                                            // Request AES security
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                                            // Set URL for the data source
Connection con = DriverManager.getConnection(url, properties);
                                            // Create the connection
```

For the `DataSource` interface: If you create and deploy the `DataSource` object, you can set the user ID, password, and security mechanism by invoking the `DataSource.setUser`, `DataSource.setPassword`, and `DataSource.setSecurityMechanism` methods after you create the `DataSource` object. For example, use code like this to set the encrypted user ID and encrypted password security mechanism, with AES encryption:

```
import java.sql.*;                          // JDBC base
import com.ibm.db2.jcc.*;                   // IBM Data Server Driver for JDBC
                                            // and SQLJ implementation of JDBC
…
com.ibm.db2.jcc.DB2SimpleDataSource ds =
  new com.ibm.db2.jcc.DB2SimpleDataSource();
                                            // Create the DataSource object
ds.setDriverType(4);                        // Set the driver type
ds.setDatabaseName("san_jose");             // Set the location
ds.setServerName("mvs1.sj.ibm.com");
                                            // Set the server name
ds.setPortNumber(5021);                     // Set the port number
ds.setUser("db2adm");                       // Set the user ID
ds.setPassword("db2adm");                   // Set the password
ds.setSecurityMechanism(
  com.ibm.db2.jcc.DB2BaseDataSource.ENCRYPTED_USER_AND_PASSWORD_SECURITY);
                                            // Set security mechanism to
                                            // User ID and encrypted password
ds.setEncryptionAlgorithm(2);               // Request AES encryption
```

Valid characters in passwords: All characters in the ASCII range X'20' (decimal 32) through X'7E' (decimal 126) are valid in passwords, except for the following characters:

- X'20' (space) at the end of a password. The IBM Data Server Driver for JDBC and SQLJ strips space characters at the end of a password.
- X'3B' (semicolon)
- Any characters that cannot be converted to EBCDIC characters, if passwords in plain text are sent to a data server.

RACF password phrase security: If you are connecting to a Db2 for z/OS that is configured for RACF protection, and the RACF version supports RACF password phrases, you can supply a RACF password phrase for the password property value, instead of a simple password. A password phrase must conform to the following rules:

- A password phrase is a character string that can consist of mixed-case letters, numbers, and special characters, including blanks.
- The length of the password phrase can be 9 to 100 characters, or 14 to 100 characters.

  Password phrases of between 9 and 13 characters are allowed when the new-password-phrase exit (ICHPWX11) is installed on the z/OS system, and the exit allows password phrases of fewer than 14 characters.
- A password phrase must not contain the user ID, as sequential uppercase or sequential lowercase characters.
- A password phrase must contain at least two alphabetic characters (A through Z or a through z).
- A password phrase must contain at least two non-alphabetic characters (numerics, punctuation, or special characters).
- A password phrase must not contain more than two consecutive characters that are identical.
- If a single quotation mark (') is part of the password phrase, the single quotation mark must be represented as two consecutive single quotation marks ('').

Related tasks

"Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ" on page 13
A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

"Creating and deploying DataSource objects" on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

"Connecting to a data source using the DataSource interface" on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

Kerberos security under the IBM Data Server Driver for JDBC and SQLJ

JDBC support for Kerberos security is available for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

To enable JDBC support for Kerberos security, you also need to enable the following components of your software development kit (SDK) for Java:

- Java Cryptography Extension
- Java Generic Security Service (JGSS)
- Java Authentication and Authorization Service (JAAS)

See the documentation for your SDK for Java for information on how to enable these components.

There are three ways to specify Kerberos security for a connection:

- With a user ID and password
- Without a user ID or password
- With a delegated credential

Kerberos security with a user ID and password

For this case, Kerberos uses the specified user ID and password to obtain a ticket-granting ticket (TGT) that lets you authenticate to the database server.

You need to set the `user`, `password`, `kerberosServerPrincipal`, and `securityMechanism` properties. Set the `securityMechanism` property to com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY (11). The `kerberosServerPrincipal` property specifies the principal name that the database server registers with a Kerberos Key Distribution Center (KDC).

For the `DriverManager` interface: Set the user ID, password, Kerberos server, and security mechanism by setting the `user`, `password`, `kerberosServerPrincipal`, and `securityMechanism` properties in a `Properties` object, and then invoking the form of the `getConnection` method that includes the `Properties` object as a parameter. For example, use code like this to set the Kerberos security mechanism with a user ID and password:

```
import java.sql.*;                          // JDBC base
import com.ibm.db2.jcc.*;                   // IBM Data Server Driver for JDBC
                                            // and SQLJ implementation of JDBC
…
Properties properties = new Properties(); // Create a Properties object
properties.put("user", "db2adm");           // Set user ID for the connection
properties.put("password", "db2adm");       // Set password for the connection
properties.put("kerberosServerPrincipal",
  "sample/srvlsj.ibm.com@SRVLSJ.SJ.IBM.COM");
                                            // Set the Kerberos server
properties.put("securityMechanism",
  new String("" +
  com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY + ""));
                                            // Set security mechanism to
                                            // Kerberos
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                                            // Set URL for the data source
Connection con = DriverManager.getConnection(url, properties);
                                            // Create the connection
```

For the `DataSource` interface: If you create and deploy the `DataSource` object, set the Kerberos server and security mechanism by invoking the `DataSource.setKerberosServerPrincipal` and `DataSource.setSecurityMechanism` methods after you create the `DataSource` object. For example:

```
import java.sql.*;                          // JDBC base
import com.ibm.db2.jcc.*;                   // IBM Data Server Driver for JDBC
                                            // and SQLJ implementation of JDBC
…
com.ibm.db2.jcc.DB2SimpleDataSource db2ds =
  new com.ibm.db2.jcc.DB2SimpleDataSource();
                                            // Create the DataSource object
db2ds.setDriverType(4);                     // Set the driver type
db2ds.setDatabaseName("san_jose");          // Set the location
db2ds.setUser("db2adm");                    // Set the user
db2ds.setPassword("db2adm");                // Set the password
db2ds.setServerName("mvs1.sj.ibm.com");
                                            // Set the server name
db2ds.setPortNumber(5021);                  // Set the port number
db2ds.setKerberosServerPrincipal(
  "sample/srvlsj.ibm.com@SRVLSJ.SJ.IBM.COM");
                                            // Set the Kerberos server
db2ds.setSecurityMechanism(
  com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY);
```

```
                                        // Set security mechanism to
                                        // Kerberos
```

Kerberos security with no user ID or password

For this case, the Kerberos default credentials cache must contain a ticket-granting ticket (TGT) that lets you authenticate to the database server.

You need to set the `securityMechanism` property. Set the `securityMechanism` property to com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY (11). Setting the `kerberosServerPrincipal` property is optional.

For the `DriverManager` interface: Set the Kerberos server and security mechanism by setting the `kerberosServerPrincipal` and `securityMechanism` properties in a `Properties` object, and then invoking the form of the `getConnection` method that includes the `Properties` object as a parameter. For example, use code like this to set the Kerberos security mechanism without a user ID and password:

```
import java.sql.*;                      // JDBC base
import com.ibm.db2.jcc.*;               // IBM Data Server Driver for JDBC
                                        // and SQLJ implementation of JDBC
…
Properties properties = new Properties(); // Create a Properties object
properties.put("kerberosServerPrincipal",
  "sample/srvlsj.ibm.com@SRVLSJ.SJ.IBM.COM");
                                        // Set the Kerberos server
properties.put("securityMechanism",
  new String("" +
  com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY + ""));
                                        // Set security mechanism to
                                        // Kerberos
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                                        // Set URL for the data source
Connection con = DriverManager.getConnection(url, properties);
                                        // Create the connection
```

For the `DataSource` interface: If you create and deploy the `DataSource` object, set the Kerberos server and security mechanism by invoking the `DataSource.setKerberosServerPrincipal` and `DataSource.setSecurityMechanism` methods after you create the `DataSource` object. For example:

```
import java.sql.*;                      // JDBC base
import com.ibm.db2.jcc.*;               // IBM Data Server Driver for JDBC
                                        // and SQLJ implementation of JDBC
…
DB2SimpleDataSource db2ds =
  new com.ibm.db2.jcc.DB2SimpleDataSource();
                                        // Create the DataSource object
db2ds.setDriverType(4);                 // Set the driver type
db2ds.setDatabaseName("san_jose");      // Set the location
db2ds.setServerName("mvs1.sj.ibm.com");
                                        // Set the server name
db2ds.setPortNumber(5021);              // Set the port number
db2ds.setKerberosServerPrincipal(
  "sample/srvlsj.ibm.com@SRVLSJ.SJ.IBM.COM");
                                        // Set the Kerberos server
db2ds.setSecurityMechanism(
  com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY);
                                        // Set security mechanism to
                                        // Kerberos
```

Kerberos security with a delegated credential from another principal

For this case, you authenticate to the database server using a delegated credential that another principal passes to you.

You need to set the `kerberosServerPrincipal`, `gssCredential`, and `securityMechanism` properties. Set the `securityMechanism` property to com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY (11).

For the `DriverManager` interface: Set the Kerberos server, delegated credential, and security mechanism by setting the `kerberosServerPrincipal`, and `securityMechanism` properties in a `Properties` object. Then invoke the form of the `getConnection` method that includes the `Properties` object as a parameter. For example, use code like this to set the Kerberos security mechanism without a user ID and password:

```
import java.sql.*;                          // JDBC base
import com.ibm.db2.jcc.*;                   // IBM Data Server Driver for JDBC
                                            // and SQLJ implementation of JDBC
…
Properties properties = new Properties(); // Create a Properties object
properties.put("kerberosServerPrincipal",
  “sample/srvlsj.ibm.com@SRVLSJ.SJ.IBM.COM");
                                            // Set the Kerberos server
properties.put("gssCredential",delegatedCredential);
                                            // Set the delegated credential
properties.put("securityMechanism",
  new String("" +
    com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY + ""));
                                            // Set security mechanism to
                                            // Kerberos
String url = "jdbc:db2://mvs1.sj.ibm.com:5021/san_jose";
                                            // Set URL for the data source
Connection con = DriverManager.getConnection(url, properties);
                                            // Create the connection
```

For the `DataSource` interface: If you create and deploy the `DataSource` object, set the Kerberos server, delegated credential, and security mechanism by invoking the `DataSource.setKerberosServerPrincipal`, `DataSource.setGssCredential`, and `DataSource.setSecurityMechanism` methods after you create the `DataSource` object. For example:

```
DB2SimpleDataSource db2ds = new com.ibm.db2.jcc.DB2SimpleDataSource();
                                              // Create the DataSource object
db2ds.setDriverType(4);                       // Set the driver type
db2ds.setDatabaseName("san_jose");            // Set the location
db2ds.setServerName("mvs1.sj.ibm.com");  // Set the server name
db2ds.setPortNumber(5021);                    // Set the port number
db2ds.setKerberosServerPrincipal(
  "sample/srvlsj.ibm.com@SRVLSJ.SJ.IBM.COM");
                                              // Set the Kerberos server
db2ds.setGssCredential(delegatedCredential);
                                              // Set the delegated credential
db2ds.setSecurityMechanism(
  com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY);
                                              // Set security mechanism to
                                              // Kerberos
```

Related tasks

“Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ” on page 13
A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

“Creating and deploying DataSource objects” on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

“Connecting to a data source using the DataSource interface” on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

“Properties for the IBM Data Server Driver for JDBC and SQLJ” on page 223

IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

Requirements for Kerberos security under the IBM Data Server Driver for JDBC and SQLJ

To set up the Kerberos security environment for the IBM Data Server Driver for JDBC and SQLJ, you need to set JDBC driver properties and Kerberos Java Authentication and Authorization Service (JAAS) properties.

Basic requirements

Specify the location of the Java Authentication and Authorization Service (JAAS) login configuration file and Kerberos configuration file in your JVM properties settings. For example, specify settings like these in the JVM properties file:

```
java.security.auth.login.config=path1/jaas.conf
java.security.krb5.conf=path2/krb5.conf
```

Set IBM Data Server Driver for JDBC and SQLJ properties:

- Set the `securityMechanism` property to com.ibm.db2.jcc.DB2BaseDataSource.KERBEROS_SECURITY or 11.
- Set the `user` and `password` properties if you are using Kerberos security with user and password authentication.

The JAAS login module name that is used by the IBM Data Server Driver for JDBC and SQLJ depends on whether you specify the `user` property name. If you do not specify the `user` property name, the login module name is specified by the configuration named `com.ibm.security.jgss.krb5.initiate` for an IBM JVM, or `com.sun.security.jgss.krb5.initiate` for an Oracle JVM. If you specify the `user` property name, the JAAS login module name is specified through a JaasClient in the JAAS configuration file. The preferred method is to specify the `user` property name, and to specify the JAAS login module name through a JaasClient.

JAAS configuration keywords

The following examples show some common JAAS configuration keywords that you need to set. You can find complete explanations of keywords here:

- JAAS login module options for IBM SDK, Java Technology Edition
- JAAS login module options for Java Platform, Standard Edition and Java Development Kit

Include this entry to indicate that the JAAS login module is required:

- For an IBM JVM:

```
JaasClient {
 com.ibm.security.auth.module.Krb5LoginModule required;
}
```

- For an Oracle JVM:

```
JaasClient {
 com.sun.security.auth.module.Krb5LoginModule required;
}
```

The IBM Data Server Driver for JDBC and SQLJ does not put a ticket in the ticket cache. To specify in the JAAS login module that the default ticket cache will be used, include one of the following entries:

- For an IBM JVM:

```
JaasClient {
 com.ibm.security.auth.module.Krb5LoginModule required useDefaultCcache=true;
}
```

- For an Oracle JVM:

```
JaasClient {
 com.sun.security.auth.module.Krb5LoginModule required useTicketCache=true
doNotPrompt=true;
}
```

To specify in the JAAS login module that a specific ticket cache will be used, include one of the following entries:

- For an IBM JVM:

```
JaasClient {
 com.ibm.security.auth.module.Krb5LoginModule required useCcache="url1";
}
```

- For an Oracle JVM:

```
JaasClient {
 com.sun.security.auth.module.Krb5LoginModule required useTicketCache=true
 ticketCache="url1" doNotPrompt=true;
}
```

To specify in the JAAS login module that a Kerberos key table file will be used, include one of the following entries:

- For an IBM JVM:

```
JaasClient {
 com.ibm.security.auth.module.Krb5LoginModule required credsType=both
 useKeytab="url2" principal="kerberos-principal-domain";
}
```

- For an Oracle JVM:

```
JaasClient {
 com.sun.security.auth.module.Krb5LoginModule required useKeyTab=true
 keyTab="url2" principal="kerberos-principal-domain" doNotPrompt=true;
}
```

In the previous examples, *url1* and *url2* have the following formats:

- The *url1* format, for the ticket cache file location, is:
  - For a Linux or UNIX environment: FILE:*full path to file*

    For example: `useCcache="FILE:/folder1/folder2/mycachefile"`
  - For a Windows environment: FILE:*drive letter*:*full path to file*

    For example: `useCcache="FILE:c:/folder1/folder2/mycachefile"`
- The *url2* format, for the key table file location, is:
  - For a Linux or UNIX environment: *full path to file*

    For example: `useKeytab="/folder3/folder4/mykeytabfile"`
  - For a Windows environment: *drive letter*:*full path to file*

    For example: `useKeytab="c:/folder3/folder4/mykeytabfile"`

Related reference

“Properties for the IBM Data Server Driver for JDBC and SQLJ” on page 223

IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

IBM Data Server Driver for JDBC and SQLJ trusted context support

The IBM Data Server Driver for JDBC and SQLJ provides methods that allow you to establish and use trusted connections in Java programs.

Trusted connections are supported for:

- IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to:
  - Db2 on Linux, UNIX, and Windows systems Version 9.5 or later
  - Db2 for z/OS Version 9.1 or later
  - IBM Informix Version 11.70 or later
- IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS Version 9.1 or later

A three-tiered application model consists of a database server, a middleware server such as WebSphere Application Server, and end users. With this model, the middleware server is responsible for accessing the database server on behalf of end users. Trusted context support ensures that an end user's database identity and database privileges are used when the middleware server performs any database requests on behalf of that end user.

A trusted context is an object that the database administrator defines that contains a system authorization ID and a set of trust attributes. Currently, a database connection is the only type of context that is supported. The trust attributes identify a set of characteristics of a connection that are required for the connection to be considered a trusted connection. The relationship between a database connection and a trusted context is established when the connection to the database server is first created, and that relationship remains for the life of the database connection.

After a trusted context is defined, and an initial trusted connection to the data server is made, the middleware server can use that database connection under a different user without reauthenticating the new user at the database server.

To avoid vulnerability to security breaches, an application server that uses these trusted methods should not use untrusted connection methods.

The `DB2ConnectionPoolDataSource` class provides several versions of the `getDB2TrustedPooledConnection` method, and the `DB2XADataSource` class provides several versions of the `getDB2TrustedXAConnection` method, which allow an application server to establish the initial trusted connection. You choose a method based on the types of connection properties that you pass and whether you use Kerberos security. When an application server calls one of these methods, the IBM Data Server Driver for JDBC and SQLJ returns an Object[] array with two elements:

- The first element contains a connection instance for the initial connection.
- The second element contains a unique cookie for the connection instance. The cookie is generated by the JDBC driver and is used for authentication during subsequent connection reuse.

The `DB2PooledConnection` class provides several versions of the `getDB2Connection` method, and the `DB2Connection` class provides several versions of the `reuseDB2Connection` method, which allow an application server to reuse an existing trusted connection on behalf of a new user. The application server uses the method to pass the following items to the new user:

- The cookie from the initial connection
- New connection properties for the reused connection

The JDBC driver checks that the supplied cookie matches the cookie of the underlying trusted physical connection, to ensure that the connection request originates from the application server that established the trusted physical connection. If the cookies match, the connection becomes available for immediate use by this new user, with the new properties.

Example: Obtain the initial trusted connection:

```
// Create a DB2ConnectionPoolDataSource instance
com.ibm.db2.jcc.DB2ConnectionPoolDataSource dataSource =
  new com.ibm.db2.jcc.DB2ConnectionPoolDataSource();
// Set properties for this instance
dataSource.setDatabaseName ("STLEC1");
dataSource.setServerName ("v7ec167.svl.ibm.com");
dataSource.setDriverType (4);
dataSource.setPortNumber(446);
java.util.Properties properties = new java.util.Properties();
// Set other properties using
// properties.put("property", "value");
// Supply the user ID and password for the connection
String user = "user";
String password = "password";
// Call getDB2TrustedPooledConnection to get the trusted connection
// instance and the cookie for the connection
Object[] objects = dataSource.getDB2TrustedPooledConnection(
                         user,password, properties);
```

Example: Reuse an existing trusted connection:

```
// The first item that was obtained from the previous getDB2TrustedPooledConnection
// call is a connection object. Cast it to a PooledConnection object.
javax.sql.PooledConnection pooledCon =
  (javax.sql.PooledConnection)objects[0];
properties = new java.util.Properties();
// Set new properties for the reused object using
// properties.put("property", "value");
// The second item that was obtained from the previous getDB2TrustedPooledConnection
// call is the cookie for the connection. Cast it as a byte array.
byte[] cookie = ((byte[])(objects[1]);
// Supply the user ID for the new connection.
String newUser = "newuser";
// Supply the password for the new connection
// Use null when authentication is not required
String newPassword = null;
// Supply the name of a mapping service that maps a workstation user
// ID to a z/OS RACF ID
String userRegistry = "registry";
// Do not supply any security token data to be traced.
byte[] userSecTkn = null;
// Do not supply a previous user ID.
String originalUser = null;
// Call getDB2Connection to get the connection object for the new
// user.
java.sql.Connection con =
  ((com.ibm.db2.jcc.DB2PooledConnection)pooledCon).getDB2Connection(
     cookie,newUser,newPassword,userRegistry,userSecTkn,originalUser,properties);
```

Related tasks

“Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ” on page 13
A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

“Creating and deploying DataSource objects” on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

“Connecting to a data source using the DataSource interface” on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

“Properties for the IBM Data Server Driver for JDBC and SQLJ” on page 223

IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

IBM Data Server Driver for JDBC and SQLJ support for SSL

The IBM Data Server Driver for JDBC and SQLJ provides support for the Secure Sockets Layer (SSL) through the Java Secure Socket Extension (JSSE).

You can use SSL support in your Java applications if you use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 for z/OS Version 9 or later, to Db2 on Linux, UNIX, and Windows systems Version 9.1, Fix Pack 2 or later, or to IBM Informix Version 11.50 or later.

If you use SSL support for a connection to a Db2 for z/OS data server, and the z/OS version is V1.8, V1.9, or V1.10, the appropriate PTF for APAR PK72201 must be applied to Communication Server for z/OS IP Services.

Connections to all supported data servers can use server authentication. For server authentication, the server sends a certificate to the client, and the client confirms the identity of the server. Connections to Db2 for z/OS data servers can also use client authentication. For client authentication, the client sends a certificate to the server, and the server confirms the identity of the client. Client authentication can be used with SSL encryption or without SSL encryption.

To use SSL connections, you need to:

- Configure connections to the data server to use SSL.
- Configure your Java Runtime Environment to use SSL.

Related concepts

"Certificate authentication under the IBM Data Server Driver for JDBC and SQLJ" on page 585
The IBM Data Server Driver for JDBC and SQLJ provides support for client support for certificate authentication for connections to Db2 for z/OS Version 10 or later data servers.

Related tasks

"Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ" on page 13
A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

"Creating and deploying DataSource objects" on page 23
JDBC versions starting with version 2.0 provide the `DataSource` interface for connecting to a data source. Using the `DataSource` interface is the preferred way to connect to a data source.

"Connecting to a data source using the DataSource interface" on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Configuring the Db2 server for SSL (Managing Security)

Related reference

"Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223
IBM Data Server Driver for JDBC and SQLJ properties define how the connection to a particular data source should be made. Most properties can be set for a `DataSource` object or for a `Connection` object.

Related information

Db2 for z/OS: Configuring TLS/SSL for Secure Client-Server Communications (IBM Redbooks)

DB2 9 for z/OS: Configuring SSL for Secure Client-Server Communications (IBM Redbooks)

Configuring connections under the IBM Data Server Driver for JDBC and SQLJ to use SSL

To configure database connections under the IBM Data Server Driver for JDBC and SQLJ to use SSL, you need to set the DB2BaseDataSource.sslConnection property to true.

Before you begin

Before a connection to a data source can use SSL, the port to which the application connects must be configured in the database server as the SSL listener port.

Procedure

1. Set DB2BaseDataSource.sslConnection on a Connection or DataSource instance. Alternatively, set the db2.jcc.override.sslConnection or db2.jcc.sslConnection configuration parameter on the driver instance.
2. Optional: Set the location of the truststore and the truststore password. The truststore location can be set without the password, but it is best to set both values.
   a) Set DB2BaseDataSource.sslTrustStoreLocation on a Connection or DataSource instance to identify the location of the truststore. Alternatively, set the db2.jcc.override.sslTrustStoreLocation or db2.jcc.sslTrustStoreLocation configuration parameter on the driver instance.

      Setting the sslTrustStoreLocation property is an alternative to setting the Java javax.net.ssl.trustStore property. If you set DB2BaseDataSource.sslTrustStoreLocation, javax.net.ssl.trustStore is not used.
   b) Optional: Set DB2BaseDataSource.sslTrustStorePassword on a Connection or DataSource instance to identify the truststore password. Alternatively, set the db2.jcc.override.sslTrustStorePassword or db2.jcc.sslTrustStorePassword configuration parameter on the driver instance.

      Setting the sslTrustStorePassword property is an alternative to setting the Java javax.net.ssl.trustStorePassword property. If you set DB2BaseDataSource.sslTrustStorePassword, javax.net.ssl.trustStorePassword is not used.
3. Optional: Set DB2BaseDataSource.sslCipherSuites on a Connection or DataSource instance, if you do not want to use the default cipher suites that are enabled in the JRE (Java Runtime Environment). The driver enables only the cipher suites that you set.
4. Optional: Set the location of the keystore, the keystore password, and the keystore type. These parameters are applicable only for mutual authentication or client certificate authentication, which is enabled only in Db2 for z/OS.
   a) Set DB2BaseDataSource.sslKeyStoreLocation on a Connection or DataSource instance to identify the location of the keystore. Alternatively, set the db2.jcc.override.sslKeyStoreLocation or db2.jcc.sslKeyStoreLocation configuration parameter on the driver instance. Setting the sslKeyStoreLocation property is an alternative to setting the Java javax.net.ssl.keyStore property. If you set DB2BaseDataSource.sslKeyStoreLocation, javax.net.ssl.keyStore is not used.
   b) Set DB2BaseDataSource.sslKeyStorePassword on a Connection or DataSource instance to identify the keystore password. Alternatively, you can set the db2.jcc.override.sslKeyStorePassword or db2.jcc.sslKeyStorePassword configuration parameter on the driver instance. Setting the sslKeyStorePassword property is an alternative to setting the Java javax.net.ssl.keyStorePassword property. If you set DB2BaseDataSource.sslKeyStorePassword, javax.net.ssl.keyStorePassword is not used.
   c) Set DB2BaseDataSource.sslKeyStoreType on a Connection or DataSource instance to identify the keystore type. Alternatively, set the db2.jcc.override.sslKeyStoreType or db2.jcc.sslKeyStoreType configuration parameter on the driver

instance. Setting the sslKeyStoreType property is an alternative to setting the Java javax.net.ssl.keyStoreType property. If you set DB2BaseDataSource.sslKeyStoreType, javax.net.ssl.keyStoreType is not used.

5. Optional: For a connection to a Db2 for z/OS data server, set DB2BaseDataSource.sslTrustStoreType on a Connection or DataSource to specify the type of sslTrustStore. Alternatively, set the db2.jcc.override.sslTrustStoreType or db2.jcc.sslTrustStoreType configuration parameter on the driver instance.
6. Optional: Set DB2BaseDataSource.keyUsage on a Connection or DataSource to select the keyUsage based certificates from WINDOWS-MY of keyStore type. The PKI Card supports WINDOWS-MY type keyStore and WINDOWS-ROOT of trustStore type. Alternatively, set the db2.jcc.override.keyUsage or db2.jcc.keyUsage configuration parameter on the driver instance. The keyUsage is only for client certificate selection. It doesn't apply on server certificate for server certificate authentication.

   If DataSource or Connection is configured with securityMechanism TLS_CLIENT_CERTIFICATE_SECURITY, then keyUsage is applied on connection object to select the client certificate. If DataSource or Connection is not configured with securityMechanism TLS_CLIENT_CERTIFICATE_SECURITY, the JCC driver ignores keyUsage and proceeds with the default settings for an SSL connection.
7. Optional: Set DB2BaseDataSource.sslCertLocation on a Connection or DataSource to specify the location of a trusted certificate file.

   Alternatively, you can set the db2.jcc.override.sslCertLocation or db2.jcc.sslCertLocation configuration parameter on the driver instance.

   If sslConnection property is set to true, and both sslCertLocation and sslTrustStoreLocation properties are configured, IBM Data Server Driver for JDBC and SQLJ gives precedence to the sslCertLocation property and ignores the sslTruststoreLocation configuration. Therefore, only the certificate that is supplied through sslCertLocation is considered trusted for an SSL connection with a Db2 server.

Example

The following example demonstrates how to set the sslConnection property on a Connection instance:

```
java.util.Properties properties = new java.util.Properties();
properties.put("user", "xxxx");
properties.put("password", "yyyy");
properties.put("sslConnection", "true");
java.sql.Connection con =
  java.sql.DriverManager.getConnection(url, properties);
```

Configuring the IBM Data Server Driver for JDBC and SQLJ to use RACF key rings for SSL certificates

For an IBM Data Server Driver for JDBC and SQLJ connection that uses SSL, you can use RACF key rings to store server certificates for SSL connections.

Before you begin

Configure connections under the IBM Data Server Driver for JDBC and SQLJ to use SSL.

Procedure

1. Set the **sslTrustStoreType** property to "JCERACFKS" using the setSSLTrustStoreLocation method:

   ```
   ((com.ibm.db2.jcc.DB2BaseDataSource)ds).setSSLTrustStoreLocation("JCERACFKS");
   ```
2. Set the **sslTrustStoreLocation** property using the setSslTrustStoreLocation method:

```
((com.ibm.db2.jcc.DB2BaseDataSource)
ds).setSslTrustStoreLocation(safkeyring://racf-id/ring-id);
```

3. Set the crypto provider package on the JVM:

```
Djava.protocol.handler.pkgs=com.ibm.crypto.provider
```

Examples

The following examples assume that you have specified the JVM system property java.protocol.handler.pkgs as a JVM argument:

```
-Djava.protocol.handler.pkgs=com.ibm.crypto.provider
```

- Configuring the driver to use RACF key rings for SSL certificates using the `DataSource` interface:

```
com.ibm.db2.jcc.DB2SimpleDataSource ds = new
com.ibm.db2.jcc.DB2SimpleDataSource();
ds.setDriverType(4);
ds.setDatabaseName("DBNAME");
ds.setServerName("host");
ds.setPortNumber(448);
ds.setUser("dbuser");
ds.setPassword("dbpassword");
ds.setSSLConnection (true);
// enable SSLds.setSSLTrustStoreType ("JCERACFKS");
// use JCERACFKS type oftruststoreds.setSslTrustStoreLocation
(safkeyring://racf-id/ring-id);                // URL to the RACF key ring store
      ds.setSslTrustStorePassword("password"); // Password to the RACF key ring:
                                               // Must be "password"
      storejava.sql.Connection con = ds.getConnection ();
```

- Configuring the driver to use RACF key rings for SSL certificates using the `DriverManager` interface:

```
String connectionUrl = "jdbc:db2://host:448/DBNAME:" +
                                "sslConnection=true;" +
                                "sslTrustStoreType=JCERACFKS;" +
                                "sslTrustStoreLocation=safkeyring:
                                 //<racfid>/<ringid>;"+
                                "sslTrustStorePassword=password";
java.sql.Connection con =
 DriverManager.getConnection (connectionURL, "dbuser","dbpassword");
```

Configuring the Java Runtime Environment to use SSL

Before you can use Secure Sockets Layer (SSL) connections in your JDBC and SQLJ applications, you need to configure the Java Runtime Environment to use SSL. An example procedure is provided. However, the procedure might be different depending on the Java Runtime Environment that you use.

Before you begin

Before you can configure your Java Runtime Environment for SSL, you need to satisfy the following prerequisites:

- The Java Runtime Environment must include a Java security provider. The `IBMJSSE2` provider, the `IBMCAC` provider, or the `SunJSSE` provider must be installed. The `IBMJSSE2` provider is automatically installed with the IBM SDK for Java.

  Restriction: You can use the `SunJSSE` provider only with an Oracle Java Runtime Environment. The `SunJSSE` provider does not work with an IBM Java Runtime Environment.
- SSL support must be configured on the database server.

Procedure

To configure your Java Runtime Environment to use SSL, follow these steps:

1. Import a certificate from the database server to a Java truststore on the client.

Use the Java `keytool` utility to import the certificate into the truststore.

Example: Suppose that the server certificate is stored in a file named cacerts. Issue the following `keytool` utility statement to read the certificate from file `jcc.cacert`, and store it in a truststore named cacerts.

```
keytool -import -file jcc.cacert -keystore cacerts
```

Example: Suppose that the server certificate is stored in a file named `mydbserver.arm`. Issue the following `keytool` utility statement to read the certificate from file `mydbserver.arm`, and store it in a truststore named `mynewdbclient.jks`.

```
keytool -import -trustcacerts -alias myalias -file mydbserver.arm -keystore mynewdbclient.jks
```

2. Configure the Java Runtime Environment for the Java security providers by adding entries to the `java.security` file.

   The format of a security provider entry is:

   ```
   security.provider.n=provider-package-name
   ```

   A provider with a lower value of *n* takes precedence over a provider with a higher value of *n*.

   - If you use the SunJSSE provider, add entries for the Oracle security providers to your `java.security` file.
   - If you use the IBMCAC provider, add entries for the Oracle security providers and the IBMCAC provider to your `java.security` file.

     For more information about the IBMCAC provider, see IBM Common Access Card (CAC) provider for Java.
   - If you use the IBMJSSE2 provider, follow these steps:
     - If you do not need to operate in FIPS-compliant mode:

       Ensure that entries for the IBMJSSE2 provider and the IBMJCE provider are in the `java.security` file. The `java.security` file that is shipped with the IBM SDK for Java contains entries for those providers.
     - If you need to operate in FIPS-compliant mode:
       - Add an entry for the IBMJCEFIPS provider to your `java.security` file before the entry for the IBMJCE provider. Do not remove the entry for the IBMJCE provider.
       - Enable FIPS mode in the IBMJSSE2 provider. See step "3" on page 584.

     Restriction: If you use the IBMJSSE2 provider on the Solaris operating system, you need to include an entry for the SunJSSE provider before entries for the IBMJCE, IBMJCEFIPS, or IBMJSSE2 providers.

Example: If you need to run in FIPS-compliant mode, and you enabled FIPS mode in the IBMJSSE2 provider, use a `java.security` file similar to this example:

```
# Set the Java security providers
security.provider.1=com.ibm.jsse2.IBMJSSEProvider2
security.provider.2=com.ibm.crypto.fips.provider.IBMJCEFIPS
security.provider.3=com.ibm.crypto.provider.IBMJCE
security.provider.4=com.ibm.security.jgss.IBMJGSSProvider
security.provider.5=com.ibm.security.cert.IBMCertPath
security.provider.6=com.ibm.security.sasl.IBMSASL
```

Example: If you are using the SunJSSE provider, use a `java.security` file similar to this example:

```
# Set the Java security providers
security.provider.1=sun.security.provider.Sun
security.provider.2=com.sun.rsajca.Provider
security.provider.3=com.sun.crypto.provider.SunJCE
security.provider.4=com.sun.net.ssl.internal.ssl.Provider
```

Example: If you are using the IBMCAC provider, use a `java.security` file similar to this example:

```
# Set the Java security providers
security.provider.1=sun.security.provider.Sun
security.provider.2=com.sun.rsajca.Provider
security.provider.3=com.sun.crypto.provider.SunJCE
security.provider.4=com.sun.net.ssl.internal.ssl.Provider
security.provider.10=com.ibm.security.capi.IBMCAC
```

3. If you plan to use the IBM Data Server Driver for JDBC and SQLJ in FIPS-compliant mode, you need to set the `com.ibm.jsse2.JSSEFIPS` Java system property:

   ```
   com.ibm.jsse2.JSSEFIPS=true
   ```

   Restriction: Non-FIPS-mode JSSE applications cannot run in a JVM that is in FIPS mode.

   Restriction: When the IBMJSSE2 provider runs in FIPS mode, it cannot use hardware cryptography.
4. Configure the Java Runtime Environment for the SSL socket factory providers by adding entries to the `java.security` file. This step is not necessary if you are using the SunJSSE provider and the Java Runtime Environment, 7 or later.

   The format of SSL socket factory provider entries is shown:

   ```
   ssl.SocketFactory.provider=provider-package-name
   ssl.ServerSocketFactory.provider=provider-package-name
   ```

   Specify the SSL socket factory provider for the Java security provider that you are using.

   Example: When you enable FIPS mode in the IBMJSSE2 provider, include SSL socket factory provider entries in the `java.security` file:

   ```
   # Set the SSL socket factory provider
   ssl.SocketFactory.provider=com.ibm.jsse2.SSLSocketFactoryImpl
   ssl.ServerSocketFactory.provider=com.ibm.jsse2.SSLServerSocketFactoryImpl
   ```

   Example: When you enable FIPS mode in the IBMJSSE2 provider, include SSL socket factory provider entries in the `java.security` file:

   ```
   # Set the SSL socket factory provider
   ssl.SocketFactory.provider=com.ibm.fips.jsse.JSSESocketFactory
   ssl.ServerSocketFactory.provider=com.ibm.fips.jsse.JSSEServerSocketFactory
   ```

   Example: When you use the SunJSSE provider, and the Java Runtime Environment, 6 or earlier, include SSL socket factory provider entries:

   ```
   # Set the SSL socket factory provider
   ssl.SocketFactory.provider=com.sun.net.ssl.internal.ssl.SSLSocketFactoryImpl
   ssl.ServerSocketFactory.provider=com.sun.net.ssl.internal.ssl.SSLServerSocketFactoryImpl
   ```
5. Configure Java system properties to use the truststore.

   To do that, set the following Java system properties:

   `javax.net.ssl.trustStore`
   Specifies the name of the truststore that you specified with the -keystore parameter in the keytool utility in step “1” on page 582.

   If the IBM Data Server Driver for JDBC and SQLJ property DB2BaseDataSource.sslTrustStoreLocation, db2.jcc.override.sslTrustStoreLocation, or db2.jcc.sslTrustStoreLocation is set, its value overrides the javax.net.ssl.trustStore property value.

   `javax.net.ssl.trustStorePassword` (optional)
   Specifies the password for the truststore. You do not need to set a truststore password. However, if you do not set the password, you cannot protect the integrity of the truststore.

   If the IBM Data Server Driver for JDBC and SQLJ property DB2BaseDataSource.sslTrustStorePassword, db2.jcc.override.sslTrustStorePassword, or

db2.jcc.sslTrustStorePassword is set, its value overrides the javax.net.ssl.trustStore property value.

If you are using a trusted certificate file (if DB2BaseDataSource.sslCertLocation, db2.jcc.override.sslCertLocation, or db2.jcc.sslCertLocation is set), the `javax.net.ssl.trustStore` and `javax.net.ssl.trustStorePassword` values are not used.

Example: One way that you can set Java system properties is to specify them as the arguments of the -D option when you run a Java application. Suppose that you want to run a Java application that is named MySSL.java, which accesses a data source by using an SSL connection. If you defined a truststore named cacerts, then the following command sets the truststore name when you run the application.

```
java -Djavax.net.ssl.trustStore=cacerts MySSL
```

6. To enable the IBMCAC provider, override the default truststore and keystore definitions:

```
-Djavax.net.ssl.trustStoreType=Windows-ROOT
-Djavax.net.ssl.keyStoreType=Windows-MY
```

Certificate authentication under the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ provides support for client support for certificate authentication for connections to Db2 for z/OS Version 10 or later data servers.

Client certificate authentication security on a Db2 for z/OS data server supports the use of digital certificates for mutual authentication by requesters and servers. By using z/OS digital certificates, the Secure Socket Layer (SSL) protocol supports server and client authentication during the handshake phase. A data server can validate the certificates of a client at the server, which prevents the client from obtaining a secure connection without an installation-approved certificate. The authentication of the remote client's digital certificate is performed by Application Transparent Transport Layer Security (AT-TLS) that is provided with the z/OS Communications Server TCP/IP stack.

The IBM Data Server Driver for JDBC and SQLJ supports certificate authentication for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

You enable IBM Data Server Driver for JDBC and SQLJ certificate authentication by specifying `DB2BaseDataSource.TLS_CLIENT_CERTIFICATE_SECURITY` as the value of the securityMechanism `Connection` or `DataSource` property. If the target data server supports client certificate authentication, and the mutual authentication succeeds, the driver passes a valid `Connection` object to the application. If the data server does not support client certificate authentication, or the connection was not authenticated using AT-TLS and SSL, the driver throws `DisconnectException`.

You can use certificate authentication with or without a user ID or a password. If the application does not provide a user ID or password, authentication is performed at the network layer only. If a user ID or password is provided, authentication is performed at the network layer and the data server layer.

To use SSL encryption with certificate authentication, you can set the sslConnection `Connection` or `DataSource` property or the db2.jcc.override.sslConnection or db2.jcc.sslConnection configuration property to `true`.

The following example demonstrates how to enable certificate authentication and user ID and password security in a JDBC application.

```
com.ibm.db2.jcc.DB2SimpleDataSource dataSource = new
  com.ibm.db2.jcc.DB2SimpleDataSource();
// Specify certificate authentication
dataSource.setSecurityMechanism
(com.ibm.db2.jcc.DB2BaseDataSource.TLS_CLIENT_CERTIFICATE_SECURITY);
// Set a user ID and password to be passed to the data server
((com.ibm.db2.jcc.DB2BaseDataSource)dataSource).setUser("sysadm");
dataSource.setPassword("password”);
// Identify the SSL truststore, keystore and their passwords
```

```
System.setProperty("javax.net.ssl.trustStore","c:/temp/SSL/cacerts");
System.setProperty("javax.net.ssl.trustStorePassword","password");
System.setProperty("javax.net.ssl.keyStore","c:/temp/SSL/myKS");
System.setProperty("javax.net.ssl.keyStorePassword","123456");
…
// Create a connection
con = dataSource.getConnection ();
```

Related information

Db2 for z/OS: Configuring TLS/SSL for Secure Client-Server Communications (IBM Redbooks)

Token authentication under the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ provides client support for token authentication for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity to Db2 on Linux, UNIX, and Windows systems.

Token authentication allows an application to provide a generalized token that is used for authentication at the data server. A token type string identifies the type of the token so that the data server can validate the token. The token type must be supported by the data server. Currently, JWT (JSON Web Tokens) is the only supported token type. The token is used instead of a user ID and password, and contains all of the information that is needed to authenticate the user. Token authentication is available with Db2 on Linux, UNIX, and Windows systems, Version 11.5 Mod Pack 4 or later, and with the IBM Data Server Driver for JDBC and SQLJ, version 4.27.22 or later.

You enable IBM Data Server Driver for JDBC and SQLJ token authentication by specifying `DB2BaseDataSource.TOKEN_SECURITY` (19) as the value of the securityMechanism property. If the target data server supports token authentication, the driver passes a valid `Connection` object to the application. If the data server does not support token authentication, the driver throws a `DisconnectException`.

To enable token authentication for a connection, you must specify a token with the accessToken property, and a token type with the accessTokenType property. When you use token authentication, you cannot specify a value for the user property or the password property.

Use of SSL encryption with token authentication is recommended. To use SSL encryption with token authentication, set the sslConnection property to `true`.

The following example demonstrates how to enable token security for connections that use a DB2SimpleDataSource object. In the example, the accessToken, accessTokenType, and securityMechanism properties are set on the DB2SimpleDataSource object.

```
DB2SimpleDataSource dataSource;
dataSource.setDriverType(4);
dataSource.setDatabaseName("BLUDB");
dataSource.setServerName("host-name-or-IP-address");
dataSource.setPortNumber(50001);
dataSource.setSslConnection(true);
dataSource.setSecurityMechanism(com.ibm.db2.jcc.DB2BaseDataSource.TOKEN_SECURITY);
dataSource.setAccessToken("access-token");
dataSource.setAccessTokenType("JWT");
Connection conn = dataSource.getConnection();
```

The following example demonstrates how to use the DriverManager interface to create a connection that uses token authentication. In the example, the accessToken, accessTokenType, and securityMechanism properties are set in the *url* parameter of the DriverManager.getConnection method invocation.

```
Connection conn = DriverManager.getConnection(
"jdbc:db2://host-name-or-IP-address:50001/BLUDB:" +
"accessToken=access-token;accessTokenType=JWT;" +
"securityMechanism=19;sslConnection=true");
```

The following example demonstrates how to enable token security for connections that use a DB2XADataSource object. In the example, the accessToken, accessTokenType, and securityMechanism

property values are set on the DB2XADataSource object. In the getDB2XAConnection method invocation, the *user* and *password* fields must be null.

```
DB2XADataSource xads = new DB2XADataSource();
props = new java.util.Properties();
xads.setDriverType(4);
xads.setDatabaseName("dbname");
xads.setServerName("hostname");
xads.setPortNumber(port);
xads.setSecurityMechanism(com.ibm.db2.jcc.DB2BaseDataSource.TOKEN_SECURITY);
xads.setAccessToken("access-token");
xads.setAccessTokenType("JWT");
DB2XAConnection xaconn = xads.getDB2XAConnection(null, null, props);
```

The following example demonstrates how to enable token security for connections that use a DB2XADataSource object. In the example, the securityMechanism property value for token security is set on the DB2XADataSource object, and the accessToken and accessTokenType property values are set on a java.util.Properties object that is passed to getDB2XAConnection. In the getDB2XAConnection method invocation, the *user* and *password* fields must be null.

```
DB2XADataSource xads = new DB2XADataSource();
props = new java.util.Properties();
xads.setDriverType(4);
xads.setDatabaseName("dbname");
xads.setServerName("hostname");
xads.setPortNumber(port);
xads.setSecurityMechanism(com.ibm.db2.jcc.DB2BaseDataSource.TOKEN_SECURITY);
props.put("accessToken","access-token");
props.put("accessTokenType","JWT");
DB2XAConnection xaconn = xads.getDB2XAConnection(null, null, props);
```

Related reference

Configuring token authentication in a Db2 client

Security for preparing SQLJ applications with the IBM Data Server Driver for JDBC and SQLJ

You can provide security during SQLJ application preparation by allowing users to customize applications only and limiting access to a specific set of tables during customization. If the target data server is Db2 for z/OS, you can also provide security by allowing customers to prepare but not execute applications.

Allowing users to customize only

You can use one of the following techniques to allow a set of users to customize SQLJ applications, but not to bind or run those applications:

- **Create a database system for customization only (recommended solution):** Follow these steps:
  1. Create a new Db2 subsystem. This is the customization-only system.
  2. On the customization-only system, define all the tables and views that are accessed by the SQLJ applications. The table or view definitions must be the same as the definitions on the Db2 subsystem where the application will be bound and will run (the bind-and-run system). Executing the DESCRIBE statement on the tables or views must give the same results on the customization-only system and the bind-and-run system.
  3. On the customization-only system, grant the necessary table or view privileges to users who will customize SQLJ applications.
  4. On the customization-only system, users run the sqlj command with the -compile=true option to create Java byte codes and serialized profiles for their programs. Then they run the db2sqljcustomize command with the -automaticbind NO option to create customized serialized profiles.
  5. Copy the java byte code files and customized serialized profiles to the bind-and-run system.

6. A user with authority to bind packages on the bind-and-run system runs the db2sqljbind command on the customized serialized profiles that were copied from the customization-only system.

- **Use a stored procedure to do customization:** Write a Java stored procedure that customizes serialized profiles and binds packages for SQLJ applications on behalf of the end user. This Java stored procedure needs to use a JDBC driver package that was bound with one of the DYNAMICRULES options that causes dynamic SQL to be performed under a different user ID from the end user's authorization ID. For example, you might use the DYNAMICRULES option DEFINEBIND or DEFINERUN to execute dynamic SQL under the authorization ID of the creator of the Java stored procedure. You need to grant EXECUTE authority on the stored procedure to users who need to do SQLJ customization.

  The stored does the following things:

  1. Receives the compiled SQLJ program and serialized profiles in BLOB input parameters
  2. Copies the input parameters to its file system
  3. Runs db2sqljcustomize to customize the serialized profiles and bind the packages for the SQLJ program
  4. Returns the customized serialized profiles in output parameters
- **Use a stand-alone program to do customization:** This technique involves writing a program that performs the same steps as a Java stored procedure that customizes serialized profiles and binds packages for SQLJ applications on behalf of the end user. However, instead of running the program as a stored procedure, you run the program as a stand-alone program under a library server.

Allowing users to customize and bind only

If the target data server is Db2 for z/OS Version 10 or later, you can allow users to customize and bind SQLJ applications, but not to execute the SQL statements in them, by granting those users the EXPLAIN privilege.

Restricting table access during customization

When you customize serialized profiles, you should do online checking, to give the application program information about the data types and lengths of table columns that the program accesses. By default, customization includes online checking.

Online checking requires that the user who customizes a serialized profile has authorization to execute PREPARE and DESCRIBE statements against SQL statements in the SQLJ program. That authorization includes the SELECT privilege on tables and views that are accessed by the SQL statements. If SQL statements contain unqualified table names, the qualifier that is used during online checking is the value of the db2sqljcustomize -qualifier parameter. Therefore, for online checking of tables and views with unqualified names in an SQLJ application, you can grant the SELECT privilege only on tables and views with a qualifier that matches the value of the -qualifier parameter.

Chapter 13. Java client support for high availability on IBM data servers

Client applications that connect to Db2 on Linux, UNIX, and Windows systems, Db2 for z/OS, or IBM Informix can easily take advantage of the high availability features of those data servers.

Client applications can use the following high availability features:

- Automatic client reroute

  Automatic client reroute capability is available on all IBM data servers. Automatic client reroute uses information that is provided by the data servers to redirect client applications from a server that experiences an outage to an alternate server. Automatic client reroute enables applications to continue their work with minimal interruption. Redirection of work to an alternate server is called *failover*.

  For connections to Db2 for z/OS data servers, automatic client reroute is part of the workload balancing feature. In general, for Db2 for z/OS, automatic client reroute should not be enabled without workload balancing.

- Client affinities

  Client affinities is a failover solution that is controlled completely by the client. It is intended for situations in which you need to connect to a particular primary server. If an outage occurs during the connection to the primary server, you use client affinities to enforce a specific order for failover to alternate servers.

  In a Db2 for z/OS data sharing environment, client affinities provides control over where work is executed. However, sysplex workload balancing provides more efficient use of your Db2 for z/OS resources by ensuring that work goes to the member that has the best chance to meet your WLM goals.

- Workload balancing

  Workload balancing is available on all IBM data servers. Workload balancing ensures that work is distributed efficiently among servers in an IBM Informix high-availability cluster, Db2 for z/OS data sharing group, or Db2 on Linux, UNIX, and Windows systems Db2 pureScale instance.

The following table provides links to server-side information about these features.

Table 114. Server-side information on high availability

Data server	Related topics
Db2 on Linux, UNIX, and Windows systems	• Db2 pureScale: Db2 pureScale Feature road map • Automatic client reroute: Db2 automatic client reroute roadmap
IBM Informix	Connection management through the Connection Manager
Db2 for z/OS	Communicating with data sharing groups (Db2 Data Sharing Planning and Administration)

Important: For connections to Db2 for z/OS, this information discusses direct connections to Db2 for z/OS. For information about high availability for connections through Db2 Connect Server, see the Db2 Connect documentation.

© Copyright IBM Corp. 1998, 2017

Java client support for high availability for connections to Db2 on Linux, UNIX, and Windows systems servers

Db2 on Linux, UNIX, and Windows systems servers provide high availability for client applications, through workload balancing and automatic client reroute. This support is available for applications that use Java clients (JDBC, SQLJ, or pureQuery), as well as non-Java clients (ODBC, CLI, .NET, OLE DB, PHP, Ruby, or embedded SQL).

For Java clients, high availability support requires IBM Data Server Driver for JDBC and SQLJ version 3.58 or 4.8, or later.

High availability support for connections to Db2 on Linux, UNIX, and Windows systems servers includes:

Automatic client reroute
This support enables a client to recover from a failure by attempting to reconnect to the database through an alternate server. Reconnection to another server is called *failover*. For Java clients, automatic client reroute support is always enabled.

Automatic client reroute capability for Java applications is available with IBM Data Server Driver for JDBC and SQLJ type 4 connectivity or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

Servers can provide automatic client reroute capability in any of the following ways:

- Several servers are configured in a Db2 pureScale instance. A connection to a database is a connection to a member of that Db2 pureScale instance. Failover involves reconnection to another member of the Db2 pureScale instance. This environment requires that clients use TCP/IP to connect to the Db2 pureScale instance.
- A Db2 pureScale instance and an alternate server are defined for a database. Failover first involves reconnection to another member of the Db2 pureScale instance. Failover to the alternate server is attempted only if no member of the Db2 pureScale instance is available.
- A Db2 pureScale instance is defined for the primary server, and another Db2 pureScale instance is defined for the alternate server. Failover first involves reconnection to another member of the primary Db2 pureScale instance. Failover to the alternate Db2 pureScale instance is attempted only if no member of the primary instance is available.
- A database is defined on a single server. The configuration for that database includes specification of an alternate server. Failover involves reconnection to the alternate server.

For Java, client applications, failover for automatic client reroute can be *seamless* or *non-seamless*. With non-seamless failover, when the client application reconnects to another server, an error is always returned to the application, to indicate that failover (connection to the alternate server) occurred. With seamless failover, the driver does not return an error if a connection failure and successful reconnection to an alternate server occur during execution of the first SQL statement in a transaction.

In a Db2 pureScale instance, automatic client reroute support can be used without workload balancing or with workload balancing.

You can configure automatic client reroute to include the following additional capabilities:

You can configure automatic client reroute to include the following additional capability:

Client affinities
Client affinities is an automatic client reroute solution that is controlled completely by the client. It is intended for situations in which you need to connect to a particular primary server. If an outage occurs during the connection to the primary server, you use client affinities to enforce a specific order for failover to alternate servers.

Alternate group support
Alternate group support allows the IBM Data Server Driver for JDBC and SQLJ to execute an application workload on one group at a time. A group can be a primary group or one of several alternate groups. Each group is a Db2 on Linux, UNIX, and Windows systems instance, which can be single-member instance, or a multiple-member instance, such a Db2 pureScale instance.

Workload balancing
Workload balancing can improve availability of a Db2 pureScale instance.

With workload balancing, a Db2 pureScale instance ensures that work is distributed efficiently among members.

Workload balancing for Java applications is available with IBM Data Server Driver for JDBC and SQLJ type 4 connectivity only.

Java clients on any operating system support workload balancing. The connection from the client to the Db2 pureScale instance must use TCP/IP.

When workload balancing is enabled, the client gets frequent status information about the members of the Db2 pureScale instance through a server list. The client caches the server list and uses the information in it to determine the member to which the next transaction should be routed.

For Java applications, when JNDI is used, the cached server list can be shared by multiple JVMs for the first connection. However workload balancing is always performed within the context of a single JVM.

Db2 on Linux, UNIX, and Windows systems supports two types of workload balancing:

Connection-level workload balancing
Connection-level workload balancing is performed at connection boundaries. It is not supported for Java clients.

Transaction-level workload balancing
Transaction-level workload balancing is performed at transaction boundaries. Client support for transaction-level workload balancing is disabled by default for clients that connect to Db2 on Linux, UNIX, and Windows systems.

Configuration of Db2 on Linux, UNIX, and Windows systems automatic client reroute support for Java clients

For connections to Db2 on Linux, UNIX, and Windows systems databases, the process for configuration of automatic client reroute support on Java clients is the same for connections to a non-Db2 pureScale environment and a Db2 pureScale environment.

Automatic client reroute support for Java client applications that connect to Db2 on Linux, UNIX, and Windows systems works for connections that are obtained using the `javax.sql.DataSource`, `javax.sql.ConnectionPoolDataSource`, `javax.sql.XADataSource`, or `java.sql.DriverManager` interface.

To configure automatic client reroute on a IBM Data Server Driver for JDBC and SQLJ client:

1. Set the appropriate properties to specify the primary and alternate server addresses to use if the first connection fails.
   - If your application is using the `DriverManager` interface for connections:
     a. Specify the server name and port number of the primary server that you want to use in the connection URL.
     b. Set the clientRerouteAlternateServerName and clientRerouteAlternatePortNumber properties to the server name and port number of the alternate server that you want to use.

   Restriction: Automatic client reroute support for connections that are made with the `DriverManager` interface has the following restrictions:

   – Alternate server information is shared between `DriverManager` connections only if you create the connections with the same URL and properties.
   – You cannot set the clientRerouteServerListJNDIName property or the clientRerouteServerListJNDIContext properties for a `DriverManager` connection.
   – Automatic client reroute is not enabled for default connections (jdbc:default:connection).

- If your application is using the DataSource interface for connections, use one or both of the following techniques:
  - Set the server names and port numbers in DataSource properties:
    a. Set the serverName and portNumber properties to the server name and port number of the primary server that you want to use.
    b. Set the clientRerouteAlternateServerName and clientRerouteAlternatePortNumber properties to the server name and port number of the alternate server that you want to use.
  - Configure JNDI for automatic client reroute by using a DB2ClientRerouteServerList instance to identify the primary server and alternate server.
    a. Create an instance of DB2ClientRerouteServerList.

       DB2ClientRerouteServerList is a serializable Java bean with the following properties:

Property name	Data type
com.ibm.db2.jcc.DB2ClientRerouteServerList.alternateServerName	String[]
com.ibm.db2.jcc.DB2ClientRerouteServerList.alternatePortNumber	int[]
com.ibm.db2.jcc.DB2ClientRerouteServerList.primaryServerName	String[]
com.ibm.db2.jcc.DB2ClientRerouteServerList.primaryPortNumber	int[]

       getXXX and setXXX methods are defined for each property.
    b. Set the com.ibm.db2.jcc.DB2ClientRerouteServerList.primaryServerName and com.ibm.db2.jcc.DB2ClientRerouteServerList.primaryPortNumber properties to the server name and port number of the primary server that you want to use.
    c. Set the com.ibm.db2.jcc.DB2ClientRerouteServerList.alternateServerName and com.ibm.db2.jcc.DB2ClientRerouteServerList.alternatePortNumber properties to the server names and port numbers of the alternate server that you want to use.
    d. To make the DB2ClientRerouteServerList persistent:
       i) Bind the DB2ClientRerouteServerList instance to the JNDI registry.
       ii) Assign the JNDI name of the DB2ClientRerouteServerList object to the IBM Data Server Driver for JDBC and SQLJ clientRerouteServerListJNDIName property.
       iii) Assign the name of the JNDI context that is used for binding and lookup of the DB2ClientRerouteServerList instance to the clientRerouteServerListJNDIContext property.

    When a DataSource is configured to use JNDI for storing automatic client reroute alternate information, the standard server and port properties of the DataSource are not used for a getConnection request. Instead, the primary server address is obtained from the transient clientRerouteServerList information. If the JNDI store is not available due to a JNDI bind or lookup failure, the IBM Data Server Driver for JDBC and SQLJ attempts to make a connection using the standard server and port properties of the DataSource. Warnings are accumulated to indicate that a JNDI bind or lookup failure occurred.

    After a failover:

    - The IBM Data Server Driver for JDBC and SQLJ attempts to propagate the updated server information to the JNDI store.
    - primaryServerName and primaryPortNumber values that are specified in DB2ClientRerouteServerList are used for the connection. If primaryServerName is not specified, the serverName and portNumber values for the DataSource instance are used.

  If you configure DataSource properties as well as configuring JNDI for automatic client reroute, the DataSource properties have precedence over the JNDI configuration.
2. Set properties to control the number of retries, time between retries, and the frequency with which the server list is refreshed.

The following properties control retry behavior for automatic client reroute.

maxRetriesForClientReroute
The maximum number of connection retries for automatic client reroute.

When client affinities support is not configured, if maxRetriesForClientReroute or retryIntervalForClientReroute is not set, the default behavior is that the connection is retried for 10 minutes, with a wait time between retries that increases as the length of time from the first retry increases.

When client affinities is configured, the default for maxRetriesForClientReroute is 3.

retryIntervalForClientReroute
The number of seconds between consecutive connection retries.

When client affinities support is not configured, if retryIntervalForClientReroute or maxRetriesForClientReroute is not set, the default behavior is that the connection is retried for 10 minutes, with a wait time between retries that increases as the length of time from the first retry increases.

When client affinities is configured, the default for retryIntervalForClientReroute is 0 (no wait).

Related tasks

"Connecting to a data source using the DriverManager interface with the IBM Data Server Driver for JDBC and SQLJ" on page 13
A JDBC application can establish a connection to a data source using the JDBC `DriverManager` interface, which is part of the `java.sql` package.

"Connecting to a data source using the DataSource interface" on page 20
If your applications need to be portable among data sources, you should use the `DataSource` interface.

Related reference

"Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224
Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Example of enabling Db2 on Linux, UNIX, and Windows systems automatic client reroute support in Java applications

Java client setup for Db2 on Linux, UNIX, and Windows systems automatic client reroute support includes setting several IBM Data Server Driver for JDBC and SQLJ properties.

The following example demonstrates setting up Java client applications for Db2 on Linux, UNIX, and Windows systems automatic client reroute support.

Suppose that your installation has a primary server and an alternate server with the following server names and port numbers:

Server name	Port number
srv1.sj.ibm.com	50000
srv3.sj.ibm.com	50002

The following code sets up `DataSource` properties in an application so that the application connects to srv1.sj.ibm.com as the primary server, and srv3.sj.ibm.com as the alternative server. That is, if srv1.sj.ibm.com is down during the initial connection, the driver should connect to srv3.sj.ibm.com.

```
ds.setDriverType(4);
ds.setServerName("srv1.sj.ibm.com");
ds.setPortNumber("50000");
ds.setClientRerouteAlternateServerName("srv3.sj.ibm.com");
ds.setClientRerouteAlternatePortNumber("50002");
```

The following code configures JNDI for automatic client reroute. It creates an instance of `DB2ClientRerouteServerList`, binds that instance to the JNDI registry, and assigns the JNDI name of the `DB2ClientRerouteServerList` object to the clientRerouteServerListJNDIName property.

```
// Create a starting context for naming operations
InitialContext registry = new InitialContext();
// Create a DB2ClientRerouteServerList object
DB2ClientRerouteServerList address = new DB2ClientRerouteServerList();

// Set the port number and server name for the primary server
address.setPrimaryPortNumber(50000);
address.setPrimaryServerName("srv1.sj.ibm.com");

// Set the  port number and server name for the alternate server
int[] port = {50002};
String[] server = {"srv3.sj.ibm.com"};
address.setAlternatePortNumber(port);
address.setAlternateServerName(server);

registry.rebind("serverList", address);
// Assign the JNDI name of the DB2ClientRerouteServerList object to the
// clientRerouteServerListJNDIName property
datasource.setClientRerouteServerListJNDIName("serverList");
```

Related concepts

"Configuration of Db2 on Linux, UNIX, and Windows systems automatic client reroute support for Java clients" on page 591
For connections to Db2 on Linux, UNIX, and Windows systems databases, the process for configuration of automatic client reroute support on Java clients is the same for connections to a non-Db2 pureScale environment and a Db2 pureScale environment.

Related reference

"Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224
Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Configuration of Db2 on Linux, UNIX, and Windows systems workload balancing support for Java clients

To configure a IBM Data Server Driver for JDBC and SQLJ client application that connects to a Db2 on Linux, UNIX, and Windows systems Db2 pureScale instance for workload balancing, you need to connect to a member of the Db2 pureScale instance, and set the properties that enable workload balancing and the maximum number of connections.

Java client applications support transaction-level workload balancing. They do not support connection-level workload balancing. Workload balancing is supported only for connections to a Db2 pureScale instance.

Workload balancing support for Java client applications that connect to Db2 on Linux, UNIX, and Windows systems works for connections that are obtained using the `javax.sql.DataSource`, `javax.sql.ConnectionPoolDataSource`, `javax.sql.XADataSource`, or `java.sql.DriverManager` interface.

Restriction: Workload balancing support for connections that are made with the `DriverManager` interface has the following restrictions:

- Alternate server information is shared between `DriverManager` connections only if you create the connections with the same URL and properties.
- You cannot set the clientRerouteServerListJNDIName property or the clientRerouteServerListJNDIContext properties for a `DriverManager` connection.
- Workload balancing is not enabled for default connections (jdbc:default:connection).

The following table describes the basic property settings for enabling Db2 on Linux, UNIX, and Windows systems workload balancing for Java applications.

Table 115. Basic settings to enable workload support in Java applications

IBM Data Server Driver for JDBC and SQLJ setting	Value
enableSysplexWLB property	true
maxTransportObjects property	The maximum number of connections that the requester can make to the Db2 pureScale instance
Connection address: server	The IP address of a member of a Db2 pureScale instance"1" on page 595
Connection address: port	The SQL port number for the Db2 pureScale instance"1" on page 595
Connection address: database	The database name

Note:

1. Alternatively, you can use a distributor, such as Websphere Application Server Network Deployment, or multihomed DNS to establish the initial connection to the database.
   - For a distributor, you specify the IP address and port number of the distributor. The distributor analyzes the current workload distribution, and uses that information to forward the connection request to one of the members of the Db2 pureScale instance.
   - For multihomed DNS, you specify an IP address and port number that can resolve to the IP address and port number of any member of the Db2 pureScale instance. Multihomed DNS processing selects a member based on some criterion, such as simple round-robin selection or member workload distribution.

If you want to fine-tune Db2 on Linux, UNIX, and Windows systems workload balancing support, global configuration properties are available. The properties for the IBM Data Server Driver for JDBC and SQLJ are listed in the following table.

Table 116. Configuration properties for fine-tuning Db2 on Linux, UNIX, and Windows systems workload balancing support for connections from the IBM Data Server Driver for JDBC and SQLJ

IBM Data Server Driver for JDBC and SQLJ configuration property	Description
db2.jcc.maxRefreshInterval	Specifies the maximum amount of time in seconds between refreshes of the client copy of the server list that is used for workload balancing. The default is 10. The minimum valid value is 1.
db2.jcc.maxTransportObjectIdleTime	Specifies the maximum elapsed time in number of seconds before an idle transport is dropped. The default is 10. The minimum supported value is 0.
db2.jcc.maxTransportObjectWaitTime	Specifies the number of seconds that the client will wait for a transport to become available. The default is 1. The minimum supported value is 0.
db2.jcc.minTransportObjects	Specifies the lower limit for the number of transport objects in a global transport object pool. The default value is 0. Any value that is less than or equal to 0 means that the global transport object pool can become empty.

Example of enabling Db2 on Linux, UNIX, and Windows systems workload balancing support in Java applications

Java client setup for Db2 on Linux, UNIX, and Windows systems workload balancing support includes setting several IBM Data Server Driver for JDBC and SQLJ properties.

The following example demonstrates setting up Java client applications for Db2 on Linux, UNIX, and Windows systems workload balancing support.

Before you can set up the client, the servers to which the client connects must be configured in a Db2 pureScale instance.

Follow these steps to set up the client:

1. Verify that the IBM Data Server Driver for JDBC and SQLJ is at the correct level to support workload balancing by following these steps:
   a. Issue the following command in a command line window:

      ```
      java com.ibm.db2.jcc.DB2Jcc -version
      ```

   b. Find a line in the output like this, and check that *nnn* is 3.58 or later.

   c. `[jcc] Driver: IBM Data Server Driver for JDBC and SQLJ Architecture` *`nnn xxx`*
2. Set IBM Data Server Driver for JDBC and SQLJ properties to enable the connection concentrator or workload balancing:
   a. Set these `Connection` or `DataSource` properties. Alternatively, you can set their equivalent global configuration properties.
      - enableSysplexWLB
      - maxTransportObjects
   b. Set the db2.jcc.maxRefreshInterval global configuration property in a DB2JccConfiguration.properties file to set the maximum refresh interval for all `DataSource` or `Connection` instances that are created under the driver.

   Start with settings similar to these:

   Table 117. Example of property settings for workload balancing for Db2 on Linux, UNIX, and Windows systems

Property	Setting
enableSysplexWLB	true
maxTransportObjects	80
db2.jcc.maxRefreshInterval	10

   The values that are specified are not intended to be recommended values. You need to determine values based on factors such as the number of physical connections that are available. The number of transport objects must be equal to or greater than the number of connection objects.
3. To fine-tune workload balancing for all `DataSource` or `Connection` instances that are created under the driver, set the db2.jcc.maxTransportObjects configuration property in a DB2JccConfiguration.properties file.

   Start with a setting similar to this one:

   ```
   db2.jcc.maxTransportObjects=1000
   ```

4. **Optional:** Specify alternate server names in the clientRerouteAlternateServername and clientRerouteAlternatePortNumber properties. This step is not necessary for enabling workload

balancing. However, specifying an alternate server list is useful to ensure that the first connection is successful if the primary server is unavailable.

Operation of automatic client reroute for connections to Db2 on Linux, UNIX, and Windows systems from Java clients

When IBM Data Server Driver for JDBC and SQLJ client reroute support is enabled, a Java application that is connected to a Db2 on Linux, UNIX, and Windows systems database can continue to run when the primary server has a failure.

Automatic client reroute for a Java application that is connected to a Db2 on Linux, UNIX, and Windows systems database operates in the following way when support for client affinities is disabled:

1. During each connection to the data source, the IBM Data Server Driver for JDBC and SQLJ obtains primary and alternate server information.
   - For the first connection to a Db2 on Linux, UNIX, and Windows systems database:
     a. If the clientRerouteAlternateServerName and clientRerouteAlternatePortNumber properties are set, the IBM Data Server Driver for JDBC and SQLJ loads those values into memory as the alternate server values, along with the primary server values serverName and portNumber.
     b. If the clientRerouteAlternateServerName and clientRerouteAlternatePortNumber properties are not set, and a JNDI store is configured by setting the property clientRerouteServerListJNDIName on the `DB2BaseDataSource`, the IBM Data Server Driver for JDBC and SQLJ loads the primary and alternate server information from the JNDI store into memory.
     c. If no `DataSource` properties are set for the alternate servers, and JNDI is not configured, the IBM Data Server Driver for JDBC and SQLJ checks DNS tables for primary and alternate server information. If DNS information exists, the IBM Data Server Driver for JDBC and SQLJ loads those values into memory.
     d. If no primary or alternate server information is available, a connection cannot be established, and the IBM Data Server Driver for JDBC and SQLJ throws an exception.
   - For subsequent connections, the IBM Data Server Driver for JDBC and SQLJ obtains primary and alternate server values from driver memory.
2. The IBM Data Server Driver for JDBC and SQLJ attempts to connect to the data source using the primary server name and port number.

   In a non-Db2 pureScale environment, the primary server is a stand-alone server. In a Db2 pureScale environment, the primary server is a member of a Db2 pureScale instance.

   If the connection is through the `DriverManager` interface, the IBM Data Server Driver for JDBC and SQLJ creates an internal `DataSource` object for automatic client reroute processing.
3. If the connection to the primary server fails:
   a. If this is the first connection, the IBM Data Server Driver for JDBC and SQLJ attempts to reconnect to a server using information that is provided by driver properties such as clientRerouteAlternateServerName and clientRerouteAlternatePortNumber.
   b. If this is not the first connection, the IBM Data Server Driver for JDBC and SQLJ attempts to make a connection using the information from the latest server list that is returned from the server.

   Connection to an alternate server is called *failover*.

   The IBM Data Server Driver for JDBC and SQLJ uses the maxRetriesForClientReroute and retryIntervalForClientReroute properties to determine how many times to retry the connection and how long to wait between retries. An attempt to connect to the primary server and alternate servers counts as one retry.
4. If the connection is not established, maxRetriesForClientReroute and retryIntervalForClientReroute are not set, and the original serverName and portNumber values that are defined on the `DataSource` are different from the serverName and portNumber values that were used for the current connection,

the connection is retried with the serverName and portNumber values that are defined on the `DataSource`.

5. If failover is successful during the initial connection, the driver generates an `SQLWarning`. If a successful failover occurs after the initial connection:
   - If seamless failover is enabled, and the following conditions are satisfied, the driver retries the transaction once on the new server, without notifying the application.
     - The enableSeamlessFailover property is set to `DB2BaseDataSource.YES` (1).
     - The connection is not in a transaction. That is, the failure occurs when the first SQL statement in the transaction is executed.
     - There are no global temporary tables in use on the server.
     - There are no open, held cursors.
   - If seamless failover is not in effect, the driver throws an `SQLException` to the application with error code -4498, to indicate to the application that the connection was automatically reestablished and the transaction was implicitly rolled back. The application can then retry its transaction without doing an explicit rollback first.

     A reason code that is returned with error code -4498 indicates whether any database server special registers that were modified during the original connection are reestablished in the failover connection.

   You can determine whether alternate server information was used in establishing the initial connection by calling the `DB2Connection.alternateWasUsedOnConnect` method.
6. After failover, driver memory is updated with new primary and alternate server information that is returned from the new primary server.

Examples

Example: Automatic client reroute to a Db2 on Linux, UNIX, and Windows systems server when maxRetriesForClientReroute and retryIntervalForClientReroute are not set: Suppose that the following properties are set for a connection to a database:

Property	Value
enableClientAffinitiesList	DB2BaseDataSource.NO (2)
serverName	host1
portNumber	port1
clientRerouteAlternateServerName	host2
clientRerouteAlternatePortNumber	port2

The following steps demonstrate an automatic client reroute scenario for a connection to a Db2 on Linux, UNIX, and Windows systems server:

1. The IBM Data Server Driver for JDBC and SQLJ loads host1:port1 into its memory as the primary server address, and host2:port2 into its memory as the alternate server address.
2. On the initial connection, the driver tries to connect to host1:port1.
3. The connection to host1:port1 fails, so the driver tries another connection to host1:port1.
4. The reconnection to host1:port1 fails, so the driver tries to connect to host2:port2.
5. The connection to host2:port2 succeeds.
6. The driver retrieves alternate server information that was received from server host2:port2, and updates its memory with that information.

   Assume that the driver receives a server list that contains host2:port2, host2a:port2a. host2:port2 is stored as the new primary server, and host2a:port2a is stored as the new alternate server. If another

communication failure is detected on this same connection, or on another connection that is created from the same `DataSource`, the driver tries to connect to host2:port2 as the new primary server. If that connection fails, the driver tries to connect to the new alternate server host2a:port2a.

7. A communication failure occurs during the connection to host2:port2.
8. The driver tries to connect to host2a:port2a.
9. The connection to host2a:port2a is successful.
10. The driver retrieves alternate server information that was received from server host2a:port2a, and updates its memory with that information.

Example: Automatic client reroute to a Db2 on Linux, UNIX, and Windows systems server in a Db2 pureScale environment, when maxRetriesForClientReroute and retryIntervalForClientReroute are not set: Suppose that the following properties are set for a connection that is established from `DataSource` A:

Property	Value
enableClientAffinitiesList	DB2BaseDataSource.NO (2)
serverName	host1
portNumber	port1

The following steps demonstrate an automatic client reroute scenario for a connection to a Db2 on Linux, UNIX, and Windows systems server:

1. Using the information in `DataSource` A, the IBM Data Server Driver for JDBC and SQLJ loads host1:port1 into its memory as the primary server address.
2. The connection to host1:port1 succeeds. Suppose that the server returns a server list that contains host1:port1 and host2:port2.
3. The driver creates a cache in memory, with an entry that specifies host2:port2 as the alternate server list for host1:port1.
4. The connection of Application A to host1:port1 fails, so the driver tries to connect to host2:port2.
5. The connection of Application A to host2:port2 succeeds. Suppose that the server returns a server list that contains host2:port2 and host2a:port2a. host2:port2 is the new primary server, and host2a:port2a is the new alternate server.
6. The driver looks for alternate server information for host2:port2 in the in-memory cache, but does not find any. It creates a new entry in the in-memory cache for host2:port2, with host2a:port2a as the alternate server list.
7. Application A completes, and the JVM exits.
8. Application B, which also uses `DataSource` A, starts.
9. A communication failure occurs when Application B tries to connect to host1:port1.
10. Application B attempts to connect to alternate server host2:port2.
11. The connection to host2:port2 succeeds. Application B continues.

Example: Automatic client reroute to a Db2 on Linux, UNIX, and Windows systems server when maxRetriesForClientReroute and retryIntervalForClientReroute are set for multiple retries: Suppose that the following properties are set for a connection to a database:

Property	Value
enableClientAffinitiesList	DB2BaseDataSource.NO (2)
serverName	host1
portNumber	port1
clientRerouteAlternateServerName	host2
clientRerouteAlternatePortNumber	port2

Property	Value
maxRetriesForClientReroute	3
retryIntervalForClientReroute	2

The following steps demonstrate an automatic client reroute scenario for a connection to a Db2 on Linux, UNIX, and Windows systems server:

1. The IBM Data Server Driver for JDBC and SQLJ loads host1:port1 into its memory as the primary server address, and host2:port2 into its memory as the alternate server address.
2. On the initial connection, the driver tries to connect to host1:port1.
3. The connection to host1:port1 fails, so the driver tries another connection to host1:port1.
4. The connection to host1:port1 fails again, so the driver tries to connect to host2:port2.
5. The connection to host2:port2 fails.
6. The driver waits two seconds.
7. The driver tries to connect to host1:port1 and fails.
8. The driver tries to connect to host2:port2 and fails.
9. The driver waits two seconds.
10. The driver tries to connect to host1:port1 and fails.
11. The driver tries to connect to host2:port2 and fails.
12. The driver waits two seconds.
13. The driver throws an `SQLException` with error code -4499.

Related concepts

"Configuration of Db2 on Linux, UNIX, and Windows systems automatic client reroute support for Java clients" on page 591

For connections to Db2 on Linux, UNIX, and Windows systems databases, the process for configuration of automatic client reroute support on Java clients is the same for connections to a non-Db2 pureScale environment and a Db2 pureScale environment.

Related reference

"Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224

Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Operation of alternate group support for connections to Db2 on Linux, UNIX, and Windows systems

Alternate group support is a high-availability feature that allows the IBM Data Server Driver for JDBC and SQLJ to execute an application workload on one group at a time. A group can be a primary group or one of several alternate groups.

Each group is a Db2 on Linux, UNIX, and Windows systems instance, which can be single-member instance, or a multiple-member instance, such as a Db2 pureScale instance.

Before you enable seamless failover to an alternate group, you need to enable automatic client reroute to an alternate group by setting `Connection` or `DataSource` property enableSysplexWLB to true. Then you indicate that seamless failover to an alternate group will be used by setting `Connection` or `DataSource` property enableAlternateGroupSeamlessACR to true.

You enable alternate group support by providing the addresses of the alternate groups in the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName `Connection` or `DataSource` properties. You provide the address of the primary group in the serverName, portNumber, and databaseName `Connection` or `DataSource` properties.

In an HADR environment, you enable alternate group support by providing the addresses of the standby clusters in the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName `Connection` or `DataSource` properties. The address for the primary connection is the address of the primary cluster.

To avoid unpredictable client reroute behavior, follow these practices:

- Do not specify the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName properties, and also execute the Db2 on Linux, UNIX, and Windows systems command UPDATE ALTERNATE SERVER FOR DATABASE on the data server.
- When you set up a Db2 pureScale instance that consists of two HADR clusters, execute the command UPDATE ALTERNATE SERVER FOR DATABASE command, but do not specify the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName properties.
- When you set up a Db2 pureScale instance that consists of more than two HADR clusters, specify the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName properties, but do not execute the command UPDATE ALTERNATE SERVER FOR DATABASE command.

Alternate group support allows failover from the primary group to any alternate group. After a connection on a `DataSource` instance fails over to an alternate group, subsequent connections on the `DataSource` instance connect directly to that alternate group. If an alternate group becomes unavailable during a connection, the connection can fail over to any other alternate group. A group is unavailable if any of the following conditions are true:

- The IBM Data Server Driver for JDBC and SQLJ receives a communication failure from all members of the group.
- The members of the group return SQL errors to the IBM Data Server Driver for JDBC and SQLJ to indicate that the driver should drop the connection to that group. For example, if the role of a primary HADR database changes to a standby role, the database server might return an SQL error to the driver that indicates that the request cannot be issued on an HADR standby database. The driver interprets that SQL error as a group failure.

Alternate group support operates in the following way:

- For the first connection, the process is as follows:
  1. After the first connection to the primary group fails, the driver attempts to connect the application to the alternate group that is specified by the first set of values in the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName properties.
  2. The driver attempts to connect to the alternate group. The number of attempts and the amount of time between retries depends on whether a cached server list exists on the client, and whether maxRetriesForClientReroute and retryIntervalForClientReroute are set:
     - If a cached server list does not exist, and maxRetriesForClientReroute and retryIntervalForClientReroute are not set, the driver makes at most five attempts to connect to the alternate group, with no time between retries.
     - If a cached server list exists, and maxRetriesForClientReroute and retryIntervalForClientReroute are not set, the driver retries the connection for up to two minutes.
     - If maxRetriesForClientReroute and retryIntervalForClientReroute are set, the driver retries the connection the number of times that is specified by maxRetriesForClientReroute, with an interval between retries that is specified by retryIntervalForClientReroute.
  3. If all attempts to connect to the first alternate group fail, the driver attempts to connect the application to the alternate group that is specified by the next set of values in the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName properties. The driver uses the same rules for the number of retries and interval between retries as it uses for the connection to the first alternate group.

     The driver continues this process until all alternate groups have been tried, or a connection has been established.

4. If a connection is not established after all alternate group members have been tried, the driver returns SQL error -4499 to the application.

- After a connection has been established, the process is as follows:

  1. If an error occurs for which automatic client reroute can be performed, the IBM Data Server Driver for JDBC and SQLJ attempts to reconnect to the same group. The amount of time that the driver spends on retries or the number of retries depends on the maxRetriesForClientReroute property setting. However, if the data server returns an SQL error that the driver interprets as a group failure, such as SQL error -1776, the driver does not retry the connection to the same group. SQL error -1776 indicates that the driver is attempting to connect to a standby instance.
  2. If reconnection to the same group is unsuccessful, the driver attempts to connect to each alternate group that is specified by the alternateGroupServerName, alternateGroupPortNumber, and alternateGroupDatabaseName properties, starting with the next alternate group in the list after the one that failed. The amount of time that the driver spends on retries or the number of retries depends on the maxRetriesForClientReroute property setting. If the last group in the alternate server list has been tried, the driver attempts to connect to the first server in the alternate group list, and continues through the list again.
  3. If a connection is not established, the driver returns SQL error -4499 to the application.

  maxRetriesForClientReroute controls the amount of time that the driver spends on retries and the number of retries in the following way:

  – If maxRetriesForClientReroute is not set, the driver tries to connect to each group in the list until one of the following events occurs:

    - The connection succeeds.
    - The connection has been retried for two minutes.
    - The data server returns SQL error -1776.

    If the connection is unsuccessful after two minutes, or if the data server returns SQL error -1776, the driver tries the connection to the next alternate server. This process continues until (2**number-of-groups*) minutes have elapsed.

  – If maxRetriesForClientReroute is set, the driver tries to connect to each group in the list until one of the following events occurs:

    - The connection succeeds.
    - The driver has attempted to connect to all members of the group the number of times that is specified by maxRetriesForClientReroute.
    - The data server returns SQL error -1776.

    If the connection is unsuccessful after the number of retries exceeds the value that is specified by maxRetriesForClientReroute, or if the data server returns SQL error -1776, the driver tries the connection to the next alternate server. This process continues until (maxRetriesForClientReroute**number-of-groups*) attempts have occurred.

Examples

Suppose that three groups are defined as shown in the following table:

Group	Server type	Members in group
A	Primary	A1, A2
B	Alternate	B1
C	Alternate	C1, C2, C3®

The address of A1 is the primary group address. The addresses of B1 and C1 are the alternate group addresses. Workload balancing and automatic client reroute are enabled.

The following example shows how properties are set on a DataSource object to enable alternate group support and define the alternate group list:

```
com.ibm.db2.jcc.DB2SimpleDataSource ds =       // Create DB2SimpleDataSource object
  new com.ibm.db2.jcc.DB2SimpleDataSource();
…                                              // Set other properties
ds.setDatabaseName("mydb2a");                  // Set primary group database
                                               // for group A
ds.setServerName("myservera.ibm.com");         // Set primary server name
                                               // for group A
ds.setPortNumber(5912);                        // Set primary port number
                                               // for group A
ds.setEnableSysplexWLB(true);                  // Enable automatic client reroute to an
                                               // alternate group by setting property
                                               // enableSysplexWLB to true
ds.setAlternateGroupDatabaseName("mydb2b,mydb2c");
                                               // Set alternate group databases
                                               // for groups B and C
ds.setAlternateGroupServerName("myserverb.ibm.com,myserverc.ibm.com");
                                               // Set alternate group server names
                                               // for groups B and C
ds.setAlternateGroupPortNumber(5912,5912);
                                               // Set alternate group port numbers
                                               // for groups B and C
```

Example: Alternate group failover when maxRetriesForClientReroute is not set: The following steps demonstrate an alternate group scenario when maxRetriesForClientReroute is not set:

1. The driver connects to group A.
2. While A1 is executing an SQL statement, A1 returns a communication error to the driver.
3. The driver unsuccessfully retries the connection to the members in group A for two minutes.
4. The driver tries the connection to group B (server B1), which is the first server in the alternate group list. The driver tries to connect for two minutes. The connection is unsuccessful.
5. The driver tries the connection to group C, which is the next server in the alternate group list.
6. The connection to group C succeeds.
7. SQL work is performed on the connection to group C.
8. While C2 is executing an SQL statement, C2 returns SQL error -1776 to the driver, indicating that it has switched to a standby role.
9. The driver retries the connection to the members in group A, which has taken over the primary role. The connection to group A succeeds.
10. While A1 is executing an SQL statement, A1 returns a communication error to the driver.
11. The driver unsuccessfully retries the connection to the members in group A for two minutes.
12. The driver unsuccessfully tries the connection to group B (server B1) for two minutes.
13. The driver unsuccessfully retries the connection to the members in group C for two minutes.
14. The driver has retried for six minutes (three groups * two minutes per group) so it returns an SQLException with SQL error -4499 to the application.

Example: Alternate group failover when maxRetriesForClientReroute is set: The following steps demonstrate an alternate group scenario when maxRetriesForClientReroute is set to 2:

1. The driver connects to group A.
2. While A1 is executing an SQL statement, A1 returns a communication error to the driver.
3. The driver unsuccessfully retries the connection to the members in group A twice.
4. The driver tries the connection to group B (server B1), which is the first server in the alternate group list. The driver tries to connect twice. The connection is unsuccessful.
5. The driver tries the connection to group C (server C1), which is the next server in the alternate group list.
6. The connection to group C succeeds.
7. SQL work is performed on the connection to group C.

8. While C2 is executing an SQL statement, C2 returns SQL error -1776 to the driver, indicating that it has switched to a standby role.
9. The driver retries the connection to the members in group A, which has taken over the primary role. The connection succeeds.
10. While A1 is executing an SQL statement, A1 returns a communication error to the driver.
11. The driver unsuccessfully retries the connection to the members in group A twice.
12. The driver unsuccessfully tries the connection to group B (server B1) twice.
13. The driver unsuccessfully retries the connection to the members in group C twice.
14. The driver has retried six times (three groups * two retries per group) so it returns an SQLException with SQL error -4499 to the application.

Application programming requirements for high availability for connections to Db2 on Linux, UNIX, and Windows systems servers

Failover for automatic client reroute can be seamless or non-seamless. If failover for connections to Db2 on Linux, UNIX, and Windows systems is not seamless, you need to add code to account for the errors that are returned when failover occurs.

If failover is non-seamless, and a connection is reestablished with the server, SQLCODE -4498 (for Java clients) or SQL30108N (for non-Java clients) is returned to the application. All work that occurred within the current transaction is rolled back. In the application, you need to:

- Check the reason code that is returned with the error. Determine whether special register settings on the failing data sharing member are carried over to the new (failover) data sharing member. Reset any special register values that are not current.
- Execute all SQL operations that occurred during the previous transaction.

The following conditions must be satisfied for failover for connections to Db2 on Linux, UNIX, and Windows systems to be seamless:

- The application programming language is Java, CLI, or .NET.
- The connection is not in a transaction. That is, the failure occurs when the first SQL statement in the transaction is executed.
- If transaction-level load balancing is enabled, the data server allows transport reuse at the end of the previous transaction.
- All global session data is closed or dropped.
- There are no open, held cursors.
- If the application uses CLI, the application cannot perform actions that require the driver to maintain a history of previously called APIs in order to replay the SQL statement. Examples of such actions are specifying data at execution time, performing compound SQL, or using array input.
- The application is not a stored procedure.
- Autocommit is not enabled. Seamless failover can occur when autocommit is enabled. However, the following situation can cause problems: Suppose that SQL work is successfully executed and committed at the data server, but the connection or server goes down before acknowledgment of the commit operation is sent back to the client. When the client re-establishes the connection, it replays the previously committed SQL statement. The result is that the SQL statement is executed twice. To avoid this situation, turn autocommit off when you enable seamless failover.

Related reference

“Error codes issued by the IBM Data Server Driver for JDBC and SQLJ” on page 503

Warning codes in the ranges +4200 to +4299, and +4450 to +4499, and error codes in the ranges -4200 to -4299, and -4450 to -4499 are reserved for the IBM Data Server Driver for JDBC and SQLJ.

Client affinities for Db2 on Linux, UNIX, and Windows systems

Client affinities is a client-only method for providing automatic client reroute capability.

Client affinities is available for applications that use CLI, .NET, or Java (IBM Data Server Driver for JDBC and SQLJ type 4 connectivity). All rerouting is controlled by the driver.

Client affinities is intended for situations in which you need to connect to a particular primary server. If an outage occurs during the connection to the primary server, you need to enforce a specific order for failover to alternate servers. You should use client affinities for automatic client reroute only if automatic client reroute that uses server failover capabilities does not work in your environment.

As part of configuration of client affinities, you specify a list of alternate servers, and the order in which connections to the alternate servers are tried. When client affinities is in use, connections are established based on the list of alternate servers instead of the host name and port number that are specified by the application. For example, if an application specifies that a connection is made to server1, but the configuration process specifies that servers should be tried in the order (server2, server3, server1), the initial connection is made to server2 instead of server1.

Failover with client affinities is seamless, if the following conditions are true:

- The connection is not in a transaction. That is, the failure occurs when the first SQL statement in the transaction is executed.
- There are no global temporary tables in use on the server.
- There are no open, held cursors.

When you use client affinities, you can specify that if the primary server returns to operation after an outage, connections return from an alternate server to the primary server on a transaction boundary. This activity is known as *failback*.

Configuration of client affinities for Java clients for Db2 on Linux, UNIX, and Windows systems connections

To enable support for client affinities in Java applications, you set properties to indicate that you want to use client affinities, and to specify the primary and alternate servers.

The following table describes the property settings for enabling client affinities for Java applications.

Table 118. Property settings to enable client affinities for Java applications

IBM Data Server Driver for JDBC and SQLJ setting	Value
enableClientAffinitiesList	DB2BaseDataSource.YES (1)
clientRerouteAlternateServerName	A comma-separated list of the primary server and alternate servers
clientRerouteAlternatePortNumber	A comma-separated list of the port numbers for the primary server and alternate servers
enableSeamlessFailover	DB2BaseDataSource.YES (1) for seamless failover; DB2BaseDataSource.NO (2) or enableSeamlessFailover not specified for no seamless failover
maxRetriesForClientReroute	The number of times to retry the connection to each server, including the primary server, after a connection to the primary server fails. The default is 3.

Table 118. Property settings to enable client affinities for Java applications (continued)

IBM Data Server Driver for JDBC and SQLJ setting	Value
retryIntervalForClientReroute	The number of seconds to wait between retries. The default is no wait.
affinityFailbackInterval	The number of seconds to wait after the first transaction boundary to fail back to the primary server. Set this value if you want to fail back to the primary server.

Related reference

"Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224

Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Example of enabling client affinities in Java clients for Db2 on Linux, UNIX, and Windows systems connections

Before you can use client affinities for automatic client reroute in Java applications, you need to set properties to indicate that you want to use client affinities, and to identify the primary alternate servers.

The following example shows how to enable client affinities for failover without failback.

Suppose that you set the following properties for a connection to a database:

Property	Value
enableClientAffinitiesList	DB2BaseDataSource.YES (1)
clientRerouteAlternateServername	host1,host2,host3
clientRerouteAlternatePortNumber	port1,port2,port3
maxRetriesForClientReroute	3
retryIntervalForClientReroute	2

Suppose that a communication failure occurs during a connection to the server that is identified by host1:port1. The following steps demonstrate automatic client reroute with client affinities.

1. The driver tries to connect to host1:port1.
2. The connection to host1:port1 fails.
3. The driver waits two seconds.
4. The driver tries to connect to host1:port1.
5. The connection to host1:port1 fails.
6. The driver waits two seconds.
7. The driver tries to connect to host1:port1.
8. The connection to host1:port1 fails.
9. The driver waits two seconds.
10. The driver tries to connect to host2:port2.
11. The connection to host2:port2 fails.
12. The driver waits two seconds.
13. The driver tries to connect to host2:port2.

14. The connection to host2:port2 fails.
15. The driver waits two seconds.
16. The driver tries to connect to host2:port2.
17. The connection to host2:port2 fails.
18. The driver waits two seconds.
19. The driver tries to connect to host3:port3.
20. The connection to host3:port3 fails.
21. The driver waits two seconds.
22. The driver tries to connect to host3:port3.
23. The connection to host3:port3 fails.
24. The driver waits two seconds.
25. The driver tries to connect to host3:port3.
26. The connection to host3:port3 fails.
27. The driver waits two seconds.
28. The driver throws an `SQLException` with error code -4499.

The following example shows how to enable client affinities for failover with failback.

Suppose that you set the following properties for a connection to a database:

Property	Value
enableClientAffinitiesList	DB2BaseDataSource.YES (1)
clientRerouteAlternateServername	host1,host2,host3
clientRerouteAlternatePortNumber	port1,port2,port3
maxRetriesForClientReroute	3
retryIntervalForClientReroute	2
affinityFailbackInterval	300

Suppose that the database administrator takes the server that is identified by host1:port1 down for maintenance after a connection is made to host1:port1. The following steps demonstrate failover to an alternate server and failback to the primary server after maintenance is complete.

1. The driver successfully connects to host1:port1 on behalf of an application.
2. The database administrator brings down host1:port1.
3. The application tries to do work on the connection.
4. The driver successfully fails over to host2:port2.
5. After a total of 200 seconds have elapsed, the work is committed.
6. After a total of 300 seconds have elapsed, the failback interval has elapsed. The driver checks whether the primary server is up. It is not up, so no failback occurs.
7. After a total of 350 seconds have elapsed, host1:port1 is brought back online.
8. The application continues to do work on host2:port2, because the latest failback interval has not elapsed.
9. After a total of 600 seconds have elapsed, the failback interval has elapsed again. The driver checks whether the primary server is up. It is now up.
10. After a total of 650 seconds have elapsed, the work is committed.
11. After a total of 651 seconds have elapsed, the application tries to start a new transaction on host2:port2. Failback to host1:port1 occurs, so the new transaction starts on host1:port1.

Related concepts

"Configuration of client affinities for Java clients for Db2 on Linux, UNIX, and Windows systems connections" on page 605
To enable support for client affinities in Java applications, you set properties to indicate that you want to use client affinities, and to specify the primary and alternate servers.

Related reference

"Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224
Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Java client direct connect support for high availability for connections to Db2 for z/OS servers

Sysplex workload balancing functionality on Db2 for z/OS servers provides high availability for client applications that connect directly to a data sharing group. Sysplex workload balancing functionality provides workload balancing and automatic client reroute capability. This support is available for applications that use Java clients (JDBC, SQLJ, or pureQuery) that use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, or non-Java clients (ODBC, CLI, .NET, OLE DB, PHP, Ruby, or embedded SQL). Workload balancing is transparent to applications.

A sysplex is a set of z/OS systems that communicate and cooperate with each other through certain multisystem hardware components and software services to process customer workloads. Db2 for z/OS subsystems on the z/OS systems in a sysplex can be configured to form a data sharing group. With data sharing, applications that run on more than one Db2 for z/OS subsystem can read from and write to the same set of data concurrently. One or more coupling facilities provide high-speed caching and lock processing for the data sharing group. The sysplex, together with the Workload Manager (WLM), dynamic virtual IP address (DVIPA), and the sysplex Distributor, allow a client to access a Db2 for z/OS database over TCP/IP with network resilience, and distribute transactions for an application in a balanced manner across members within the data sharing group.

Central to these capabilities is a server list that the data sharing group returns on connection boundaries and optionally on transaction boundaries. This list contains the IP address and WLM weight for each data sharing group member. With this information, a client can distribute transactions in a balanced manner, or identify the member to use when there is a communication failure.

The server list is returned on the first successful connection to the Db2 for z/OS data server. After the client has received the server list, the client directly accesses a data sharing group member based on information in the server list.

Db2 for z/OS provides several methods for clients to access a data sharing group. The access method that is set up for communication with the data sharing group determines whether sysplex workload balancing is possible. The following table lists the access methods and indicates whether sysplex workload balancing is possible.

Table 119. Data sharing access methods and sysplex workload balancing

Data sharing access method[“1” on page 609]	Description	sysplex workload balancing possible?
Group access	A requester uses the Db2 group IP address to make an initial connection to the Db2 for z/OS location. A connection to the data sharing group that uses the group IP address and SQL port is always successful if at least one member is started. The server list that is returned by the data sharing group contains: • A list of members that are currently active and can perform work • The WLM weight for each member The group IP address is configured using the z/OS sysplex distributor. To clients that are outside the sysplex, the sysplex distributor provides a single IP address that represents a Db2 location. In addition to providing fault tolerance, the sysplex distributor can be configured to provide connection load balancing.	Yes
Group subset access	A requester uses a location alias to make an initial connection to one of the members that is represented by the alias. A connection to the data sharing group that uses the group IP address and alias SQL port is successful if at least one member is started, and that member has its TCP/IP listener ready and has the capacity to accept new connections on the alias SQL port. The server list that is returned by the data sharing group contains: • A list of members that are currently active, can perform work, and have been configured as an alias • The WLM weight for each member The requester uses this information to connect to the member or members with the most capacity that are also associated with the location alias. Group subset access is used when requesters need to take advantage of sysplex workload balancing among a subset of members of a data sharing group.	Yes
Member-specific access	Member-specific access is used when requesters need to access only one member of a data sharing group. For member-specific access, the connection uses the member-specific IP address. For member-specific access to be used, IBM Data Server Driver for JDBC and SQLJ properties enableSysplexWLB and enableConnectionConcentrator must be set to `false`.	No

Note:

1. For more information on data sharing access methods, see TCP/IP access methods for Db2 data sharing (Db2 Data Sharing Planning and Administration).

Sysplex workload balancing includes automatic client reroute: Automatic client reroute support enables a client to recover from a failure by attempting to reconnect to the data server through any available member of a sysplex. Reconnection to another member is called *failover*. Automatic client reroute can be

seamless when the application is rerouted, and the application does not receive an error after a network failure to a data sharing member. An example of a situation in which automatic reroute can be seamless is when a member is shut down for maintenance.

For Java, CLI, or .NET client applications, failover for automatic client reroute can be *seamless* or *non-seamless*. Seamless failover means that when the application successfully reconnects to an alternate server, the server does not return an error to the application.

With seamless failover, the IBM Data Server Driver for JDBC and SQLJ sets the application environment from the old server on the new server. This environment includes special register values and global variable values.

Client direct connect support for high availability with a Db2 Connect server: Client direct connect support for high availability requires a Db2 Connect license, but does not need a Db2 Connect server. The client connects directly to Db2 for z/OS.

If you use a Db2 Connect server, but set up your environment for client high availability, you cannot take advantage of some of the features that a direct connection to Db2 for z/OS provides, such as transaction-level workload balancing or automatic client reroute capability that is provided by the sysplex.

Restriction on sysplex workload balancing and automatic client reroute: When a Java application that is connected to a Db2 for z/OS data server references or sets a global variable that is a user-defined array type or a LOB, the data server disables transaction balancing across the data sharing group. The data server prevents automatic client reroute after a member fails or is forced to shut down. The thread remains active until the application disconnects from the data server.

Configuration of sysplex workload balancing and automatic client reroute for Java clients

To configure a IBM Data Server Driver for JDBC and SQLJ client application that connects directly to Db2 for z/OS to use sysplex workload balancing and automatic client reroute, you need to use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. You also need to connect to an address that represents the data sharing group (for group access) or a subset of the data sharing group (for group subset access), and set the properties that enable workload balancing and the maximum number of connections.

You should always configure sysplex workload balancing and automatic client reroute together. When you configure a client to use sysplex workload balancing, automatic client reroute is also enabled. Therefore, you need to change property settings that are related to automatic client reroute only to fine tune automatic client reroute operation.

The following table describes the basic property settings for Java applications.

Table 120. Basic settings to enable sysplex high availability support in Java applications

Data sharing access method	IBM Data Server Driver for JDBC and SQLJ setting	Value
Group access	enableSysplexWLB property	true
Group access	Connection address:	
Group access	server	The group IP address or domain name of the data sharing group
Group access	port	The SQL port number for the Db2 location
Group access	database	The Db2 location name that is defined during installation
Group subset access	enableSysplexWLB property	true
Group subset access	Connection address:	

Table 120. Basic settings to enable sysplex high availability support in Java applications (continued)

Data sharing access method	IBM Data Server Driver for JDBC and SQLJ setting	Value
Group subset access	server	The group IP address or domain name of the data sharing group
Group subset access	port	The port number for the Db2 location alias
Group subset access	database	The name of the Db2 location alias that represents a subset of the members of the data sharing group
Group access or group subset access	commandTimeout	Specifies the maximum time in seconds that an application that runs under the IBM Data Server Driver for JDBC and SQLJ waits for any kind of request to the data server to complete before the driver throws an `SQLException`. The wait time includes time to obtain a transport, perform failover if needed, send the request, and wait for a response. The default is 0.
Group access or group subset access	connectionTimeout	Specifies the maximum time in seconds that the IBM Data Server Driver for JDBC and SQLJ waits for a reply from a data sharing group when the driver attempts to establish a connection. If the driver If the driver does not receive a reply after the amount of time that is specified by connectionTimeout, it throws an `SQLException` with SQL error code -4499. The default is 0. If connectionTimeout is set to a positive value, that value overrides any other timeout values that are set on a connection, such as loginTimeout.
Group access or group subset access	maxTransportObjects	Specifies the maximum number of connections that the requester can make to the data sharing group. The default is 1000. To determine the maxTransportObjects value, multiply the expected number of concurrent active connections to the Db2 for z/OS data sharing group by the number of members in the data sharing group.

Additional properties are available for fine tuning sysplex workload balancing and automatic client reroute. You should initially set up sysplex workload balancing using only the basic properties. In most cases, you should not need to set any of the additional properties.

The following IBM Data Server Driver for JDBC and SQLJ `Connection` or `DataSource` properties can be used to fine-tune sysplex workload balancing and automatic client reroute:

- blockingReadConnectionTimeout
- enableSeamlessFailover
- loginTimeout

The following IBM Data Server Driver for JDBC and SQLJ configuration properties can be used to fine-tune sysplex workload balancing and automatic client reroute:

- db2.jcc.maxRefreshInterval
- db2.jcc.maxTransportObjectIdleTime
- db2.jcc.maxTransportObjectWaitTime
- db2.jcc.minTransportObjects

Related reference

"IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 288
The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

"Common IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS and IBM Informix" on page 268
Some of the IBM Data Server Driver for JDBC and SQLJ properties apply to IBM Informix and Db2 for z/OS database servers.

"Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224
Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Example of enabling Db2 for z/OS sysplex workload balancing and automatic client reroute in Java applications

Java client setup for sysplex workload balancing and automatic client reroute includes setting several IBM Data Server Driver for JDBC and SQLJ properties.

The following examples demonstrate setting up Java client applications for sysplex workload balancing and automatic client reroute for high availability.

Before you can set up the client, you need to configure the following server software:

- WLM for z/OS

  For workload balancing to work efficiently, Db2 work needs to be classified. Classification applies to the first non-SET SQL statement in each transaction. Among the areas by which you need to classify the work are:

  – Authorization ID
  – Client info properties
  – Stored procedure name

    The stored procedure name is used for classification only if the first statement that is issued by the client in the transaction is an SQL CALL statement.
- Db2 for z/OS, set up for data sharing

Example of setup with WebSphere Application Server for z/OS

This example assumes that you are using WebSphere Application Server for z/OS. The minimum level of WebSphere Application Server is Version 5.1.

Follow these steps to set up the client:

1. Verify that the IBM Data Server Driver for JDBC and SQLJ is at the correct level to support the sysplex workload balancing by following these steps:

   a. Issue the following command in UNIX System Services

   ```
   java com.ibm.db2.jcc.DB2Jcc -version
   ```

   b. Find a line in the output like this, and check that *nnn* is 3.50 or later.

   ```
   [jcc] Driver: IBM Data Server Driver for JDBC and SQLJ Architecture nnn xxx
   ```

2. In the WebSphere Application Server administrative console, set the IBM Data Server Driver for JDBC and SQLJ data source property enableSysplexWLB to `true`, to enable sysplex workload balancing. Enabling sysplex workload balancing enables automatic client reroute by default.
3. In the WebSphere Application Server administrative console, set other properties for which the defaults are unacceptable. Modify these WebSphere Application Server connection properties. The following settings are recommended when enableSysplexWLB is set to `true`:

Connection property	Recommended setting	Description
Reap Time	0	Specifies the interval, in seconds, between runs of the pool maintenance thread. The Reap Time interval affects performance. Because connections are not physical connections, disabling pool maintenance by setting this value to 0 is recommended.
Aged Timeout	0	Specifies the interval in seconds before a physical connection is discarded. Setting Aged Timeout to 0 allows connections to remain in the pool indefinitely.
Purge Policy		Specifies how to purge connections when a stale connection or fatal connection error is detected. Because sysplex workload balancing isolates WebSphere Application Server from stale connections or fatal connections errors, FailingConnectionOnly is the recommended setting.

The Maximum Connections value does not need to be changed. Member Connections specifies the maximum number of physical connections that you create in your pool. It does not control the number of physical connections to a data sharing group. With sysplex workload balancing, connections are logical, and use transports to associate a connection to a data sharing member. Physical connections are managed by transport pools in the driver. The maxTransportObjects property controls the maximum number of connections to the group.

4. Optional: Set IBM Data Server Driver for JDBC and SQLJ configuration properties to fine-tune workload balancing for all `DataSource` or `Connection` instances that are created under the driver. Beginning with versions 3.63 and 4.13 of the IBM Data Server Driver for JDBC and SQLJ, the default values should work for most environments.

   Set the configuration properties in a DB2JccConfiguration.properties file by following these steps:

   a. Create a DB2JccConfiguration.properties file or edit the existing DB2JccConfiguration.properties file.
   b. Set the configuration properties in the DB2JccConfiguration.properties file:

      ```
      property=value
      ```

   c. Add the directory path for DB2JccConfiguration.properties to the WebSphere Application Server IBM Data Server Driver for JDBC and SQLJ classpath.
   d. Restart WebSphere Application Server.

Example of setup for DriverManager connections

This example assumes that you are using the `DriverManager` interface to establish a connection.

Follow these steps to set up the client:

1. Verify that the IBM Data Server Driver for JDBC and SQLJ is at the correct level to support the sysplex workload balancing and automatic client reroute by following these steps:

   a. Issue the following command in UNIX System Services

      ```
      java com.ibm.db2.jcc.DB2Jcc -version
      ```

b. Find a line in the output like this, and check that *nnn* is 3.50 or later. A minimum driver level of 3.50 is required for using sysplex workload balancing and automatic client reroute for `DriverManager` connections.

c. `[jcc] Driver: IBM Data Server Driver for JDBC and SQLJ Architecture nnn xxx`

2. Set the IBM Data Server Driver for JDBC and SQLJ `Connection` property enableSysplexWLB to enable workload balancing. Enabling sysplex workload balancing enables automatic client reroute by default. Set any other properties for which the defaults are unacceptable. For most users, the default values do not need to be changed.

```
java.util.Properties properties = new java.util.Properties();
properties.put("user", "xxxx");
properties.put("password", "yyyy");
properties.put("enableSysplexWLB", "true");
java.sql.Connection con =
  java.sql.DriverManager.getConnection(url, properties);
```

3. Optional: Set IBM Data Server Driver for JDBC and SQLJ configuration properties to fine-tune workload balancing for all `DataSource` or `Connection` instances that are created under the driver. Beginning with versions 3.63 and 4.13 of the IBM Data Server Driver for JDBC and SQLJ, the default values should work for most environments. Set the configuration properties in a DB2JccConfiguration.properties file by following these steps:

   a. Create a DB2JccConfiguration.properties file or edit the existing DB2JccConfiguration.properties file.

   b. Set the configuration properties in the DB2JccConfiguration.properties file:

   ```
   property=value
   ```

   c. Include the directory that contains DB2JccConfiguration.properties in the CLASSPATH concatenation.

Related concepts

“Configuration of sysplex workload balancing and automatic client reroute for Java clients” on page 610
To configure a IBM Data Server Driver for JDBC and SQLJ client application that connects directly to Db2 for z/OS to use sysplex workload balancing and automatic client reroute, you need to use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. You also need to connect to an address that represents the data sharing group (for group access) or a subset of the data sharing group (for group subset access), and set the properties that enable workload balancing and the maximum number of connections.

Related reference

“IBM Data Server Driver for JDBC and SQLJ configuration properties” on page 288
The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

“Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products” on page 224
Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

WebSphere Application Server configuring a data source using the administrative console

Operation of sysplex workload balancing for connections from Java clients to Db2 for z/OS servers

Sysplex workload balancing (also called transaction-level workload balancing) for connections to Db2 for z/OS contributes to high availability by balancing work among members of a data sharing group at the start of a transaction.

The following overview describes the steps that occur when a client connects to a Db2 for z/OS sysplex, and sysplex workload balancing is enabled:

1. When the application first establishes a connection using the sysplex-wide IP address, which is called the group IP address, or when a connection is reused by another connection object, the server returns

a server list that contains member workload distribution information to the IBM Data Server Driver for JDBC and SQLJ.

The default lifespan of the cached server list is 30 seconds.

2. At the start of a new transaction, the client reads the cached server list to identify a member that has untapped capacity, and looks in the transport pool for an idle transport that is tied to the under-utilized member. (An idle transport is a transport that has no associated connection object.)
   - If an idle transport is available, the client associates the connection object with the transport.
   - If, after a user-configurable timeout, no idle transport is available in the transport pool and no new transport can be allocated because the transport pool has reached its limit, an error is returned to the application.
3. When the transaction runs, it accesses the member that is tied to the transport.

   When the first SQL statement in a transaction runs, if the IBM Data Server Driver for JDBC and SQLJ receives a communication failure because the data server drops the connection or the blockingReadConnectionTimeout value was exceeded, the driver retries the SQL statement once before it reports an error. On every retry, the driver closes the existing transport, obtains a new transport and then executes the transaction.
4. When the transaction ends, the client verifies with the server that transport reuse is still allowed for the connection object.
5. If transport reuse is allowed, the server returns a list of SET statements for special registers that apply to the execution environment for the connection object.

   The client caches these statements, which it replays in order to reconstruct the execution environment when the connection object is associated with a new transport.
6. The connection object is then disassociated from the transport.
7. The client copy of the server list is refreshed when a new connection is made, or every 30 seconds.
8. When workload balancing is required for a new transaction, the client uses the same process to associate the connection object with a transport.

Operation of automatic client reroute for connections from Java clients to Db2 for z/OS

Automatic client reroute support provides failover support when an IBM data server client loses connectivity to a member of a Db2 for z/OS sysplex. Automatic client reroute enables the client to recover from a failure by attempting to reconnect to the database through any available member of the sysplex.

Automatic client reroute is enabled by default when sysplex workload balancing is enabled. Automatic client reroute should never be enabled when sysplex workload balancing is disabled.

Client support for automatic client reroute is available in IBM data server clients that have a Db2 Connect license. The Db2 Connect server is not required to perform automatic client reroute.

Automatic client reroute for connections to Db2 for z/OS operates in the following way:

1. The IBM Data Server Driver for JDBC and SQLJ uses the distributed IP address as the group IP address to establish the initial connection to the data sharing group. If the connection to the group IP address fails, the connection is retried five times, with no wait between retries.
2. After a transaction has been established:
   - If an SQL statement in the transaction fails, the application receives SQL error -30108 with reason code 2. The IBM Data Server Driver for JDBC and SQLJ does not acquire an active transport.
   - If the connection to the data server is dropped, and the automatic client reroute feature fails to execute an SQL statement, the statement receives SQL error -20542. If multiple -20542 errors occur, the underlying cause might be server-side abends or errors. The Db2 for z/OS administrator needs to investigate those abends or errors.
3. The application retries the transaction.

4. The driver attempts to acquire a transport to each member of the data sharing group in the order of their calculated priorities (WLM member weights) until a transport is acquired. The driver does not attempt to acquire a transport to the member to which the connection failed in step "2" on page 615.
5. If the driver cannot acquire a transport, the driver attempts to contact the group IP address to check for any members that have become available.
6. If the driver still cannot acquire a transport, the driver continues to execute steps "4" on page 616 and "5" on page 616 until a transport is acquired.

Related reference

"Error codes issued by the IBM Data Server Driver for JDBC and SQLJ" on page 503
Warning codes in the ranges +4200 to +4299, and +4450 to +4499, and error codes in the ranges -4200 to -4299, and -4450 to -4499 are reserved for the IBM Data Server Driver for JDBC and SQLJ.

Application programming requirements for high availability for connections from Java clients to Db2 for z/OS servers

Failover for automatic client reroute can be seamless or non-seamless. If failover for connections to Db2 for z/OS is not seamless, you need to add code to account for the errors that are returned when failover occurs.

If failover is not seamless, and a connection is reestablished with the server, SQLCODE -30108 (SQL30108N) is returned to the application. All work that occurred within the current transaction is rolled back. In the application, you need to:

- Check the reason code that is returned with the -30108 error to determine whether special register settings that were carried over from the failing data sharing member to the new (failover) data sharing member were the settings at the most recent commit point, or the settings at the point of failure. Reset any special register values that are not current.
- Execute all SQL operations that occurred since the previous commit operation.

For seamless failover to occur, the following conditions must be satisfied for direct connections to Db2 for z/OS:

- The application language is Java, CLI, or .NET.
- The connection is not in a transaction. That is, the failure occurs when the first SQL statement in the transaction is executed.
- The data server allows transport reuse at the end of the previous transaction. An exception to this condition is if transport reuse is not granted because the application was bound with KEEPDYNAMIC(YES).
- All global session data is closed or dropped.
- There are no open, held cursors.
- If the application uses CLI, the application cannot perform actions that require the driver to maintain a history of previously called APIs in order to replay the SQL statement. Examples of such actions are specifying data at execution time, performing compound SQL, or using array input.
- The application is not a stored procedure.
- The application is not running in a Federated environment.
- Two-phase commit is used, if transactions are dependent on the success of previous transactions. When a failure occurs during a commit operation, the client has no information about whether work was committed or rolled back at the server. If each transaction is dependent on the success of the previous transaction, use two-phase commit. Two-phase commit requires the use of XA support.

Seamless failover is attempted once. If a data sharing member on which seamless failover is attempted goes down, failover to another data sharing member is non-seamless.

During an attempt at seamless failover, the IBM Data Server Driver for JDBC and SQLJ returns SQL error -20542 to the calling application in situations such as the following ones:

- The target Db2 for z/OS data server is down.
- If the connection request to the target Db2 for z/OS data server is processed, the MAXDBAT subsystem parameter value will be exceeded. MAXDBAT specifies the maximum number of concurrent active threads from remote locations to the data server.
- If the connection request to the target Db2 for z/OS data server is processed, the exception threshold for the MONITOR THREADS keyword in the DSN_PROFILE_ATTRIBUTES table will be exceeded.

If multiple -20542 errors occur, the underlying cause might be server-side abends or errors. The Db2 for z/OS administrator needs to investigate those abends or errors.

Failover support with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS

When you use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, you can configure connections to a data sharing group so that when a connection to a data sharing member fails, new connections switch automatically to an alternative member of the Db2 data sharing group that is running on the same LPAR.

To enable this function, you set the ssid `Connection` or `DataSource` property, or the db2.jcc.ssid configuration property to the group attachment name or subgroup attachment name that is associated with a data sharing group. The `Connection` or `DataSource` property value overrides the configuration property value.

When a Java application uses IBM Data Server Driver for JDBC and SQLJ type 2 connectivity to connect to a data source that represents a data sharing group for which a group attachment name or subgroup attachment name is defined, the IBM Data Server Driver for JDBC and SQLJ connects to a member of the data sharing group. While the data sharing member is active, all new type 2 connections to the data sharing group also connect to that same data sharing member. If the data sharing member terminates, existing connections to that member terminate. However, when new type 2 connections to the data sharing group are requested, Db2 for z/OS connects the application to a member of the data sharing group that is active on the same LPAR.

Related concepts

“Environment variables for the IBM Data Server Driver for JDBC and SQLJ” on page 534
If you set specific environment variables, the operating system can locate the IBM Data Server Driver for JDBC and SQLJ.

Related reference

“IBM Data Server Driver for JDBC and SQLJ properties for Db2 for z/OS” on page 274
Some of the IBM Data Server Driver for JDBC and SQLJ properties apply only to Db2 for z/OS servers.

Chapter 14. JDBC and SQLJ connection pooling support

Connection pooling is supported by the IBM Data Server Driver for JDBC and SQLJ.

Connection pooling provides the following advantages over manually managing individual physical connections:

- Reduces the number of times that new connection objects are created
- Promotes connection object reuse
- Increases the speed with which applications can obtain connections
- Simplifies the task of managing connection objects

How connection pooling works

Connection pooling is a framework for caching physical data source connections, which are equivalent to data server threads. When JDBC reuses physical data source connections, the expensive operations that are required for the creation and subsequent closing of `java.sql.Connection` objects are minimized.

Without connection pooling, each `java.sql.Connection` object represents a physical connection to the data source. When the application establishes a connection to a data server, the data server creates a new physical connection to the data source. When the application calls the `java.sql.Connection.close` method, the data server terminates the physical connection to the data source.

In contrast, with connection pooling, a `java.sql.Connection` object is a temporary, logical representation of a physical data source connection. The physical data source connection can be serially reused by logical `java.sql.Connection` instances. The application can use the logical `java.sql.Connection` object in exactly the same manner as it uses a `java.sql.Connection` object when there is no connection pooling support.

With connection pooling, when a JDBC application invokes the `DataSource.getConnection` method, the data source determines whether an appropriate physical connection exists. If an appropriate physical connection exists, the data source returns a `java.sql.Connection` instance to the application. When the JDBC application invokes the `java.sql.Connection.close` method, JDBC does not close the physical data source connection. Instead, JDBC closes only JDBC resources, such as `Statement` or `ResultSet` objects. The data source returns the physical connection to the connection pool for reuse.

Types of JDBC and SQLJ support for connection pooling

Two types of connection pooling support are available:

- Connection pooling by an application server, such as WebSphere Application Server
- Connection pooling by the IBM Data Server Driver for JDBC and SQLJ

Connection pooling by an application server

The IBM Data Server Driver for JDBC and SQLJ provides a factory of pooled connections that are used by WebSphere Application Server or other application servers. The application server actually does the pooling. Connection pooling is completely transparent to a JDBC or SQLJ application.

Connection pooling by the IBM Data Server Driver for JDBC and SQLJ

Starting with version 4.29 of the IBM Data Server Driver for JDBC and SQLJ, an application can request that connections are pooled. Methods and properties are available in the `DB2ConnectionPool` class for managing pooled connections. See “DB2ConnectionPool class” on page 429 for more information.

© Copyright IBM Corp. 1998, 2017

Homogeneous or heterogeneous connection pooling

Connection pooling can be *homogeneous* or *heterogeneous*.

With homogeneous pooling, all `Connection` objects that come from a connection pool should have the same properties. The first logical `Connection` that is created with the `DataSource` has the properties that were defined for the `DataSource`. However, an application can change those properties. When a `Connection` is returned to the connection pool, an application server or a pooling module should reset the properties to their original values. However, an application server or pooling module might not reset the changed properties. The JDBC driver does not modify the properties. Therefore, depending on the application server or pool module design, a reused logical `Connection` might have the same properties as those that are defined for the `DataSource` or different properties.

With heterogeneous pooling, `Connection` objects with different properties can share the same connection pool.

Chapter 15. IBM Data Server Driver for JDBC and SQLJ statement caching

The IBM Data Server Driver for JDBC and SQLJ can use an internal statement cache to improve the performance of Java applications by caching and pooling prepared statements.

Internal statement caching is available for connections that use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, or for connections that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS.

You enable internal statement caching in any of the following ways:

- By setting one of the following properties to a positive value:
  - com.ibm.db2.jcc.DB2ConnectionPoolDataSource.maxStatements, for objects that are created using the `javax.sql.ConnectionPoolDataSource` interface.
  - com.ibm.db2.jcc.DB2XADataSource.maxStatements, for objects that are created using the `javax.sql.XADataSource` interface.
  - com.ibm.db2.jcc.DB2SimpleDataSource.maxStatements, for objects that are created using the `com.ibm.db2.jcc.DB2SimpleDataSource` interfaces.
- By setting the maxStatements property in a URL, and passing the URL to the `DriverManager.getConnection` method.

When internal statement caching is enabled, the IBM Data Server Driver for JDBC and SQLJ can cache `PreparedStatement` objects, `CallableStatement` objects, and JDBC resources that are used by SQLJ statements when those objects or resources are logically closed. When you explicitly or implicitly invoke the `close` method on a statement, you logically close the statement.

Reuse of a previously cached statement is transparent to applications. The statement cache exists for the life of an open connection. When the connection is closed, the driver deletes the statement cache and closes all pooled statements.

A logically open statement becomes ineligible for caching under either of the following circumstances:

- An exception occurs on the statement.
- JDBC 4.0 method `Statement.setPoolable(false)` is called.

When the IBM Data Server Driver for JDBC and SQLJ attempts to cache a statement, and the internal statement cache is full, the driver purges the least recently used cached statement, and inserts the new statement.

The internal statement cache is purged under the following conditions:

- A SET statement is issued that affects target objects of the SQL statement.
- A SET statement is executed that the IBM Data Server Driver for JDBC and SQLJ does not recognize.
- The IBM Data Server Driver for JDBC and SQLJ detects that a property that modifies target objects of the SQL statement was modified during connection reuse. currentSchema is an example of a property that modifies target objects of an SQL statement.

In a Java program, you can test whether the internal statement cache is enabled by issuing the `DatabaseMetaData.supportsStatementPooling` method. The method returns `true` if the internal statement cache is enabled.

The IBM Data Server Driver for JDBC and SQLJ does not check whether the definitions of target objects of statements in the internal statement cache have changed. If you execute SQL data definition language statements in an application, you need to disable internal statement caching for that application.

The internal statement cache requires extra memory. If memory becomes constrained, you can increase the JVM size, or decrease the value of maxStatements.

© Copyright IBM Corp. 1998, 2017

Related reference

“Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products” on page 224

Most of the IBM Data Server Driver for JDBC and SQLJ properties apply to all database products that the driver supports.

Chapter 16. IBM Data Server Driver for JDBC and SQLJ type 4 connectivity JDBC and SQLJ distributed transaction support

The IBM Data Server Driver for JDBC and SQLJ in the z/OS environment supports distributed transaction management when you use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

This support implements the Java 2 Platform, Enterprise Edition (J2EE) Java Transaction Service (JTS) and Java Transaction API (JTA) specifications, and conforms to the X/Open standard for global transactions (*Distributed Transaction Processing: The XA Specification*, available from http://www.opengroup.org). IBM Data Server Driver for JDBC and SQLJ distributed transaction support lets Enterprise Java Beans (EJBs) and Java servlets that run under WebSphere Application Server Version 5.01 and above participate in a distributed transaction system.

JDBC and SQLJ distributed transaction support provides similar function to JDBC and SQLJ global transaction support. However, JDBC and SQLJ global transaction support is available with IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS only.

JDBC and SQLJ distributed transaction support is available for connections to Db2 for z/OS, Db2, and DB2 for IBM i servers.

A distributed transaction system consists of a resource manager, a transaction manager, and transactional applications. The following table lists the products and programs in the z/OS environment that provide those components.

Table 121. Components of a distributed transaction system on Db2 for z/OS

Distributed transaction system component	Component function provided by
Resource manager	Db2 for z/OS or Db2
Transaction manager	WebSphere Application Server or another application server
Transactional applications	JDBC or SQLJ applications

Your client application programs that run under the IBM Data Server Driver for JDBC and SQLJ can use distributed transaction support for connections to Db2 for z/OS or Db2 servers.

In JDBC or SQLJ applications, distributed transactions are supported for connections that are established using the `DataSource` interface. A connection is normally established by the application server.

Related concepts

"JDBC and SQLJ global transaction support" on page 627
JDBC and SQLJ global transaction support lets Enterprise Java Beans (EJB) and Java servlets access Db2 for z/OS relational data within global transactions.

Example of a distributed transaction that uses JTA methods

Distributed transactions typically involve multiple connections to the same data source or different data sources, which can include data sources from different manufacturers.

The best way to demonstrate distributed transactions is to contrast them with local transactions. With local transactions, a JDBC application makes changes to a database permanent and indicates the end of a unit of work in one of the following ways:

- By calling the `Connection.commit` or `Connection.rollback` methods after executing one or more SQL statements

© Copyright IBM Corp. 1998, 2017

- By calling the `Connection.setAutoCommit(true)` method at the beginning of the application to commit changes after every SQL statement

Figure 50 on page 624 outlines code that executes local transactions.

```
con1.setAutoCommit(false);  // Set autocommit off
// execute some SQL
…
con1.commit();              // Commit the transaction
// execute some more SQL
…
con1.rollback();            // Roll back the transaction
con1.setAutoCommit(true);   // Enable commit after every SQL statement
…
// Execute some more SQL, which is automatically committed after
// every SQL statement.
```

Figure 50. Example of a local transaction

In contrast, applications that participate in distributed transactions cannot call the `Connection.commit`, `Connection.rollback`, or `Connection.setAutoCommit(true)` methods within the distributed transaction. With distributed transactions, the `Connection.commit` or `Connection.rollback` methods do not indicate transaction boundaries. Instead, your applications let the application server manage transaction boundaries.

Figure 51 on page 624 demonstrates an application that uses distributed transactions. While the code in the example is running, the application server is also executing other EJBs that are part of this same distributed transaction. When all EJBs have called `utx.commit()`, the entire distributed transaction is committed by the application server. If any of the EJBs are unsuccessful, the application server rolls back all the work done by all EJBs that are associated with the distributed transaction.

```
javax.transaction.UserTransaction utx;
// Use the begin method on a UserTransaction object to indicate
// the beginning of a distributed transaction.
utx.begin();
…
// Execute some SQL with one Connection object.
// Do not call Connection methods commit or rollback.
…
// Use the commit method on the UserTransaction object to
// drive all transaction branches to commit and indicate
// the end of the distributed transaction.

utx.commit();
…
```

Figure 51. Example of a distributed transaction under an application server

Figure 52 on page 624 illustrates a program that uses JTA methods to execute a distributed transaction. This program acts as the transaction manager and a transactional application. Two connections to two different data sources do SQL work under a single distributed transaction.

Figure 52. Example of a distributed transaction that uses the JTA

```
class XASample
{
  javax.sql.XADataSource xaDS1;
  javax.sql.XADataSource xaDS2;
  javax.sql.XAConnection xaconn1;
  javax.sql.XAConnection xaconn2;
  javax.transaction.xa.XAResource xares1;
  javax.transaction.xa.XAResource xares2;
  java.sql.Connection conn1;
  java.sql.Connection conn2;

  public static void main (String args []) throws java.sql.SQLException
  {
    XASample xat = new XASample();
    xat.runThis(args);
  }
  // As the transaction manager, this program supplies the global
  // transaction ID and the branch qualifier. The global
```

```
  // transaction ID and the branch qualifier must not be
  // equal to each other, and the combination must be unique for
  // this transaction manager.
  public void runThis(String[] args)
  {
    byte[] gtrid = new byte[] { 0x44, 0x11, 0x55, 0x66 };
    byte[] bqual = new byte[] { 0x00, 0x22, 0x00 };
    int rc1 = 0;
    int rc2 = 0;

    try
    {

      javax.naming.InitialContext context = new javax.naming.InitialContext();
      /*
        * Note that javax.sql.XADataSource is used instead of a specific
        * driver implementation such as com.ibm.db2.jcc.DB2XADataSource.
        */
      xaDS1 = (javax.sql.XADataSource)context.lookup("checkingAccounts");
      xaDS2 = (javax.sql.XADataSource)context.lookup("savingsAccounts");

      // The XADatasource contains the user ID and password.
      // Get the XAConnection object from each XADataSource
      xaconn1 = xaDS1.getXAConnection();
      xaconn2 = xaDS2.getXAConnection();

      // Get the java.sql.Connection object from each XAConnection
      conn1 = xaconn1.getConnection();
      conn2 = xaconn2.getConnection();

      // Get the XAResource object from each XAConnection
      xares1 = xaconn1.getXAResource();
      xares2 = xaconn2.getXAResource();
      // Create the Xid object for this distributed transaction.
      // This example uses the com.ibm.db2.jcc.DB2Xid implementation
      // of the Xid interface. This Xid can be used with any JDBC driver
      // that supports JTA.
      javax.transaction.xa.Xid xid1 =
                              new com.ibm.db2.jcc.DB2Xid(100, gtrid, bqual);

      // Start the distributed transaction on the two connections.
      // The two connections do NOT need to be started and ended together.
      // They might be done in different threads, along with their SQL operations.
      xares1.start(xid1, javax.transaction.xa.XAResource.TMNOFLAGS);
      xares2.start(xid1, javax.transaction.xa.XAResource.TMNOFLAGS);
…
      // Do the SQL operations on connection 1.
      // Do the SQL operations on connection 2.
…
      // Now end the distributed transaction on the two connections.
      xares1.end(xid1, javax.transaction.xa.XAResource.TMSUCCESS);
      xares2.end(xid1, javax.transaction.xa.XAResource.TMSUCCESS);

      // If connection 2 work had been done in another thread,
      // a thread.join() call would be needed here to wait until the
      // connection 2 work is done.

      try
      { // Now prepare both branches of the distributed transaction.
        // Both branches must prepare successfully before changes
        // can be committed.
        // If the distributed transaction fails, an XAException is thrown.
        rc1 = xares1.prepare(xid1);
        if(rc1 == javax.transaction.xa.XAResource.XA_OK)
        { // Prepare was successful. Prepare the second connection.
          rc2 = xares2.prepare(xid1);
          if(rc2 == javax.transaction.xa.XAResource.XA_OK)
          { // Both connections prepared successfully and neither was read-only.
            xares1.commit(xid1, false);
            xares2.commit(xid1, false);
          }
          else if(rc2 == javax.transaction.xa.XAException.XA_RDONLY)
          { // The second connection is read-only, so just commit the
            // first connection.
            xares1.commit(xid1, false);
          }
        }
        else if(rc1 == javax.transaction.xa.XAException.XA_RDONLY)
        { // SQL for the first connection is read-only (such as a SELECT).
          // The prepare committed it. Prepare the second connection.
          rc2 = xares2.prepare(xid1);
          if(rc2 == javax.transaction.xa.XAResource.XA_OK)
```

```
          { // The first connection is read-only but the second is not.
            // Commit the second connection.
            xares2.commit(xid1, false);
          }
          else if(rc2 == javax.transaction.xa.XAException.XA_RDONLY)
          { // Both connections are read-only, and both already committed,
            // so there is nothing more to do.
          }
        }
      }       catch (javax.transaction.xa.XAException xae)
      { // Distributed transaction failed, so roll it back.
        // Report XAException on prepare/commit.
        System.out.println("Distributed transaction prepare/commit failed. " +
                           "Rolling it back.");
        System.out.println("XAException error code = " + xae.errorCode);
        System.out.println("XAException message = " + xae.getMessage());
        xae.printStackTrace();
        try
        {
          xares1.rollback(xid1);
        }
        catch (javax.transaction.xa.XAException xae1)
        { // Report failure of rollback.
          System.out.println("distributed Transaction rollback xares1 failed");
          System.out.println("XAException error code = " + xae1.errorCode);
          System.out.println("XAException message = " + xae1.getMessage());
        }
        try
        {
          xares2.rollback(xid1);
        }
        catch (javax.transaction.xa.XAException xae2)
        { // Report failure of rollback.
          System.out.println("distributed Transaction rollback xares2 failed");
          System.out.println("XAException error code = " + xae2.errorCode);
          System.out.println("XAException message = " + xae2.getMessage());
        }
      }

      try
      {
        conn1.close();
        xaconn1.close();
      }
      catch (Exception e)
      {
        System.out.println("Failed to close connection 1: " + e.toString());
        e.printStackTrace();
      }
      try
      {
        conn2.close();
        xaconn2.close();
      }
      catch (Exception e)
      {
        System.out.println("Failed to close connection 2: " + e.toString());
        e.printStackTrace();
      }
    }
    catch (java.sql.SQLException sqe)
    {
      System.out.println("SQLException caught: " + sqe.getMessage());
      sqe.printStackTrace();
    }
    catch (javax.transaction.xa.XAException xae)
    {
      System.out.println("XA error is " + xae.getMessage());
      xae.printStackTrace();
    }
    catch (javax.naming.NamingException nme)
    {
      System.out.println(" Naming Exception: " + nme.getMessage());
    }
  }
}
```

Recommendation: For better performance, complete a distributed transaction before you start another distributed or local transaction.

Chapter 17. JDBC and SQLJ global transaction support

JDBC and SQLJ global transaction support lets Enterprise Java Beans (EJB) and Java servlets access Db2 for z/OS relational data within global transactions.

WebSphere Application Server provides the environment to deploy EJBs and servlets, and RRS provides the transaction management.

JDBC and SQLJ global transaction support provides similar function to JDBC and SQLJ distributed transaction support. However, JDBC and SQLJ distributed transaction support is available with IBM Data Server Driver for JDBC and SQLJ type 4 connectivity on Db2 for z/OS or Db2.

You can use global transactions in JDBC or SQLJ applications. Global transactions are supported for connections that are established using the `DriverManager` or the `DataSource` interface.

The best way to demonstrate global transactions is to contrast them with local transactions. With local transactions, you call the `commit` or `rollback` methods of the `Connection` class to make the changes to the database permanent and indicate the end of each unit or work. Alternatively, you can use the `setAutoCommit(true)` method to perform a commit operation after every SQL statement. The following code shows an example of a local transaction.

```
con1.setAutoCommit(false);  // Set autocommit off
// execute some SQL
…
con1.commit();              // Commit the transaction
// execute some more SQL
…
con1.rollback();            // Roll back the transaction
con1.setAutoCommit(true);   // Enable commit after every SQL statement
…
```

In contrast, applications cannot call the `commit`, `rollback`, or `setAutoCommit(true)` methods on the `Connection` object when the applications are in a global transaction. With global transactions, the `commit` or `rollback` methods on the `Connection` object do not indicate transaction boundaries. Instead, your applications let WebSphere manage transaction boundaries. Alternatively, you can use Db2-customized Java Transaction API (JTA) interfaces to indicate the boundaries of transactions. Although Db2 for z/OS does not implement the JTA specification, the methods for delimiting transaction boundaries are available with the JDBC driver. The following code demonstrates the use of the JTA interfaces to indicate global transaction boundaries.

```
javax.transaction.UserTransaction utx;
// Use the begin method on a UserTransaction object to indicate
// the beginning of a global transaction.
utx.begin();
…
// Execute some SQL with one Connection object.
// Do not call Connection methods commit or rollback.
…
// Use the commit method on the UserTransaction object to
// drive all transaction branches to commit and indicate
// the end of the global transaction.
utx.commit();
…
```

Related concepts

“IBM Data Server Driver for JDBC and SQLJ type 4 connectivity JDBC and SQLJ distributed transaction support” on page 623
The IBM Data Server Driver for JDBC and SQLJ in the z/OS environment supports distributed transaction management when you use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

© Copyright IBM Corp. 1998, 2017

Chapter 18. Problem diagnosis with the IBM Data Server Driver for JDBC and SQLJ

The IBM Data Server Driver for JDBC and SQLJ includes diagnostic tools and traces for diagnosing problems during connection and SQL statement execution.

Testing a data server connection

Run the DB2Jcc utility to test a connection to a data server. You provide DB2Jcc with the URL for the data server, for IBM Data Server Driver for JDBC and SQLJ type 4 connectivity or IBM Data Server Driver for JDBC and SQLJ type 2 connectivity. DB2Jcc attempts to connect to the data server, and to execute an SQL statement and a `DatabaseMetaData` method. If the connection or statement execution fails, DB2Jcc provides diagnostic information about the failure.

Collecting JDBC trace data

Use one of the following procedures to start the trace:

Procedure 1: For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity, the recommended method is to start the trace by setting the db2.jcc.override.traceFile property and the db2.jcc.t2zosTraceFile property in the IBM Data Server Driver for JDBC and SQLJ configuration properties file.

You can set the db2.jcc.tracePolling and db2.jcc.tracePollingInterval properties before you start the driver to allow you to change global configuration trace properties while the driver is running.

Procedure 2: For IBM Data Server Driver for JDBC and SQLJ type 4 connectivity, the recommended method is to start the trace by setting the db2.jcc.override.traceFile property or the db2.jcc.override.traceDirectory property in the IBM Data Server Driver for JDBC and SQLJ configuration properties file. You can set the db2.jcc.tracePolling and db2.jcc.tracePollingInterval properties before you start the driver to allow you to change global configuration trace properties while the driver is running.

Procedure 3: If you use the `DataSource` interface to connect to a data source, follow this method to start the trace:

1. Invoke the `DB2BaseDataSource.setTraceLevel` method to set the type of tracing that you need. The default trace level is `TRACE_ALL`. See "Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224 for a list of traceLevel settings. See "Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223 for information on how to specify more than one type of tracing.
2. Invoke the `DB2BaseDataSource.setJccLogWriter` method to specify the trace destination and turn the trace on.

Procedure 4:

If you use the `DataSource` interface to connect to a data source, invoke the `javax.sql.DataSource.setLogWriter` method to turn the trace on. With this method, `TRACE_ALL` is the only available trace level.

If you use the `DriverManager` interface to connect to a data source, follow this procedure to start the trace.

1. Invoke the `DriverManager.getConnection` method with the `traceLevel` property set in the *info* parameter or *url* parameter for the type of tracing that you need. The default trace level is `TRACE_ALL`. See "Common IBM Data Server Driver for JDBC and SQLJ properties for all supported database products" on page 224 for a list of traceLevel settings. See "Properties for the IBM Data Server Driver for JDBC and SQLJ" on page 223 for information on how to specify more than one type of tracing.

© Copyright IBM Corp. 1998, 2017

2. Invoke the `DriverManager.setLogWriter` method to specify the trace destination and turn the trace on.

After a connection is established, you can turn the trace off or back on, change the trace destination, or change the trace level with the `DB2Connection.setJccLogWriter` method. To turn the trace off, set the `logWriter` value to `null`.

The `logWriter` property is an object of type `java.io.PrintWriter`. If your application cannot handle `java.io.PrintWriter` objects, you can use the `traceFile` property to specify the destination of the trace output. To use the `traceFile` property, set the `logWriter` property to `null`, and set the `traceFile` property to the name of the file to which the driver writes the trace data. This file and the directory in which it resides must be writable. If the file already exists, the driver overwrites it.

Procedure 5: If you are using the `DriverManager` interface, specify the `traceFile` and `traceLevel` properties as part of the URL when you load the driver. For example:

```
String url = "jdbc:db2://sysmvs1.stl.ibm.com:5021/san_jose" +
 ":traceFile=/u/db2p/jcctrace;" +
 "traceLevel=" + com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS + ";";
```

Procedure 6: Use `DB2TraceManager` methods. The `DB2TraceManager` class provides the ability to suspend and resume tracing of any type of log writer.

Example of starting a trace using configuration properties: For a complete example of using configuration parameters to collect trace data, see "Examples of using configuration properties to start a JDBC trace" on page 635.

Trace example program: For a complete example of a program for tracing under the IBM Data Server Driver for JDBC and SQLJ, see "Example of a trace program under the IBM Data Server Driver for JDBC and SQLJ" on page 637.

Collecting SQLJ trace data during customization or bind

To collect trace data to diagnose problems during the SQLJ customization or bind process, specify the -tracelevel and -tracefile options when you run the db2sqljcustomize or db2sqljbind bind utility.

Collecting diagnostic data for a connection to a Db2 data server or data sharing group

The diagnostic data is written to a file in the directory that is specified by configuration property db2.jcc.outputDirectory. The format of the file is:

```
jccDump_timestamp_random-number_i.log
```

- *timestamp* is the timestamp when the data is written.
- *random-number* is a randomly generated positive integer.
- *i* is 0 or 1.

The maximum size of the file is approximately 2MB. When an application writes its first trace record, the driver creates a file with *i* = 0. The driver then writes trace data to the file. When the size of the file reaches approximately 2MB, the driver renames the file. The new name is the same as the original name, except that *i* is now 1. The driver continues this cycle until the application completes. Each dump entry inside the file includes the timestamp, JVM name, thread ID, data source ID, and connection ID details, so that you can locate the source of the exception.

Important:

- The maximum file size is not exactly 2MB. It might exceed 2 MB so that the last dump entry is fully logged into a single file for easier readability.
- Bringing down a JVM by killing the Java process can create .lck files on the file system. These `.lck` files must be deleted manually.

Specifying the data to collect for a data server: You specify the SQL error codes or SQL warning codes for which you want diagnostic data to be collected by setting the db2.jcc.diagLevelExceptionCode global configuration property.

If a value of db2.jcc.diagLevelExceptionCode is not specified, no diagnostic data is collected.

If db2.jcc.diagLevelExceptionCode is set to -1, diagnostic information is collected for all SQL error codes.

An SQL error code can be specified without a sign, prefixed by a minus (-) sign, or suffixed by the letter n. An SQL warning code can be prefixed by a plus (+) sign, or suffixed by the letter p.

When more than one SQL error code or SQL warning code is specified, the codes must be separated by commas.

Examples:

To collect diagnostic information for SQL error code -204, specify one of the following values:

- db2.jcc.diagLevelExceptionCode=204
- db2.jcc.diagLevelExceptionCode=-204
- db2.jcc.diagLevelExceptionCode=204n

To collect diagnostic information for SQL warning code +222, specify one of the following values:

- db2.jcc.diagLevelExceptionCode=+222
- db2.jcc.diagLevelExceptionCode=222p

Some examples of specifying collection of diagnostic information for SQL error codes -204, -30108, and -4499 are:

- db2.jcc.diagLevelExceptionCode=-204,-30108,-4499
- db2.jcc.diagLevelExceptionCode=204,30108n,4499
- db2.jcc.diagLevelExceptionCode=204n,30108,4499n

Some examples of specifying collection of diagnostic information for SQL error code -30108 and SQL warning codes +100 and +222 are:

- db2.jcc.diagLevelExceptionCode=+100,-30108,222p
- db2.jcc.diagLevelExceptionCode=100p,30108,+222

Specifying data collection for a data sharing group: When the db2.jcc.traceLevel or db2.jcc.override.traceLevel global configuration property, or the traceLevel `Connection` or `DataSource` property is set to TRACE_SYSPLEX (X'80000'), the IBM Data Server Driver for JDBC and SQLJ collects data about the data sharing group, such as the server list, automatic client reroute and workload balancing property values, transport pool statistics, and special register values.

Formatting information about an SQLJ serialized profile

The `profp` utility formats information about each SQLJ clause in a serialized profile. The format of the `profp` utility is:

Run the `profp` utility on the serialized profile for the connection in which the error occurs. If an exception is thrown, a Java stack trace is generated. You can determine which serialized profile was in use when the exception was thrown from the stack trace.

Formatting information about an SQLJ customized serialized profile

The `db2sqljprint` utility formats information about each SQLJ clause in a serialized profile that is customized for the IBM Data Server Driver for JDBC and SQLJ.

Run the db2sqljprint utility on the customized serialized profile for the connection in which the error occurs.

Related reference

“db2sqljprint - SQLJ profile printer” on page 530
db2sqljprint prints the contents of the customized version of a profile as plain text.

DB2Jcc - IBM Data Server Driver for JDBC and SQLJ diagnostic utility

DB2Jcc verifies that a data server is configured for database access.

To verify the connection, DB2Jcc connects to the specified data server, executes an SQL statement, and executes a java.sql.DatabaseMetadata method.

Authorization

The user ID under which DB2Jcc runs must have the authority to connect to the specified data server and to execute the specified SQL statement.

DB2Jcc syntax



url-spec:



sql-spec:



DB2Jcc parameters

-help
Specifies that DB2Jcc describes each of the options that it supports. If any other options are specified with -help, they are ignored.

-version
Specifies that DB2Jcc displays the driver name and version.

-info

Specifies that DB2Jcc displays IBM Data Server Driver for JDBC and SQLJ driver name and version and the corresponding Db2 Connect name and version.

For IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, DB2Jcc also displays the version of the IBM Data Server Driver for JDBC and SQLJ native libraries.

-db2ConnectVersion
Specifies that DB2Jcc displays the Db2 Connect version that corresponds to the IBM Data Server Driver for JDBC and SQLJ version.

This option is supported only for connections to Db2 for z/OS or Db2 for IBM i data servers.

license-file-path
The full path for the db2jcc_license_cisuz.jar license file.

-configuration
Specifies that DB2Jcc displays driver configuration information.

-expirationDate
Specifies that DB2Jcc displays the date on which the client license file for connections to Db2 for z/OS or Db2 for IBM i data servers expires.

-expirationDateWithLicenseType
Specifies that DB2Jcc displays:

- The date on which the client license file for connections to Db2 for z/OS or Db2 for IBM i data servers expires.
- The type of license: temporary or permanent.

-url
Specifies the URL for the data server for which the connection is being tested. The URL can be a URL for IBM Data Server Driver for JDBC and SQLJ type 2 connectivity or IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. The variable parts of the `-url` value are:

server
The domain name or IP address of the operating system on which the database server resides. *server* is used only for type 4 connectivity.

port
The TCP/IP server port number that is assigned to the data server. The default is 446. *port* is used only for type 4 connectivity.

database
A name for the database server for which the profile is to be customized.

If the connection is to a Db2 for z/OS server, *database* is the Db2 location name that is defined during installation. All characters in this value must be uppercase characters. You can determine the location name by executing the following SQL statement on the server:

```
SELECT CURRENT SERVER FROM SYSIBM.SYSDUMMY1;
```

If the connection is to a Db2 on Linux, UNIX, and Windows systems server, *database* is the database name that is defined during installation.

If the connection is to an IBM Informix data server, *database* is the database name. The name is case-insensitive. The server converts the name to lowercase.

If the connection is to an IBM Cloudscape server, the *database* is the fully-qualified name of the file that contains the database. This name must be enclosed in double quotation marks ("). For example:

```
"c:/databases/testdb"
```

-user *user-ID*
Specifies the user ID that is to be used to test the connection to the data server.

-password *password*
Specifies the password for the user ID that is to be used to test the connection to the data server.

-sql '*sql-statement*'
Specifies the SQL statement that is sent to the data server to verify the connection. If the -sql parameter is not specified, this SQL statement is sent to the data server:

```
SELECT * FROM SYSIBM.SYSDUMMY1
```

-tracing
Specifies that tracing is enabled. The trace destination is `System.out`.

If you omit the -tracing parameter, tracing is disabled.

-validateCfg
Specifies that DB2Jcc validates the keywords in the IBM data server driver configuration file (default name db2dsdriver.cfg). DB2Jcc issues errors for any invalid keywords that it finds in the file. -validateCfg applies only to connections that use IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

-path *dsdriver-config-file-path*
Specifies the full path name of the IBM Data server driver configuration file. If -path *dsdriver-config-file-path* is not specified, DB2Jcc uses the path name in the DB2DSDRIVER_CFG_PATH environment variable.

Examples

Example: Test the connection to a data server using IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. Use the default SQL statement to test the connection. Enable tracing for the test.

```
java com.ibm.db2.jcc.DB2Jcc
-url jdbc:db2://mysys.myloc.svl.ibm.com:446/MYDB
-user db2user -password db2pass -tracing
```

Example: Test the connection to a data server using IBM Data Server Driver for JDBC and SQLJ type 2 connectivity. Use the following SQL statement to test the connection:

```
SELECT COUNT(*) FROM EMPLOYEE
```

Disable tracing for the test.

```
java com.ibm.db2.jcc.DB2Jcc
-url jdbc:db2:MYDB
-user db2user -password db2pass
-sql 'SELECT COUNT(*) FROM EMPLOYEE'
```

Example: Test the connection to a data server using IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. Use the following SQL statement to test the connection:

```
SELECT '*' FROM SYSIBM.SYSDUMMY1
```

```
java com.ibm.db2.jcc.DB2Jcc
-url jdbc:db2:MYDB
-user db2user -password db2pass
-sql 'SELECT '*' FROM SYSIBM.SYSDUMMY1'
```

Example: Validate the keywords in the IBM data server configuration file whose full path name is `C:\drivercfg\mydb2dsdriver.cfg`.

```
java com.ibm.db2.jcc.DB2Jcc
-validateCfg -path C:\drivercfg\mydb2dsdriver.cfg
```

Examples of using configuration properties to start a JDBC trace

You can control tracing of JDBC applications without modifying those applications.

Example of writing trace data to one trace file for each connection

Suppose that you want to collect trace data for a program named Test.java, which uses IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. Test.java does no tracing, and you do not want to modify the program, so you enable tracing using configuration properties. You want your trace output to have the following characteristics:

- Trace information for each connection on the same `DataSource` is written to a separate trace file. Output goes into a directory named /Trace.
- Each trace file name begins with jccTrace1.
- If trace files with the same names already exist, the trace data is appended to them.

Although Test.java does not contain any code to do tracing, you want to set the configuration properties so that if the application is modified in the future to do tracing, the settings within the program will take precedence over the settings in the configuration properties. To do that, use the set of configuration properties that begin with db2.jcc, not db2.jcc.override.

The configuration property settings look like this:

- db2.jcc.traceDirectory=/Trace
- db2.jcc.traceFile=jccTrace1
- db2.jcc.traceFileAppend=true

You want the trace settings to apply only to your stand-alone program Test.java, so you create a file with these settings, and then refer to the file when you invoke the Java program by specifying the -Ddb2.jcc.propertiesFile option. Suppose that the file that contains the settings is /Test/jcc.properties. To enable tracing when you run Test.java, you issue a command like this:

```
java -Ddb2.jcc.propertiesFile=/Test/jcc.properties Test
```

Suppose that Test.java creates two connections for one `DataSource`. The program does not define a `logWriter` object, so the driver creates a global `logWriter` object for the trace output. When the program completes, the following files contain the trace data:

- /Trace/jccTrace1_global_0
- /Trace/jccTrace1_global_1

Example of doing a circular trace with a fixed number of files and fixed file size

Suppose that you want to collect trace data for a program named Test.java, which uses IBM Data Server Driver for JDBC and SQLJ type 4 connectivity. Test.java does no tracing, and you do not want to modify the program, so you enable tracing using configuration properties. You want your trace output to have the following characteristics:

- Trace information for each connection on the same `DataSource` is written to a separate set of trace files.
- The maximum number of trace files that are written for each connection is 4.
- When all trace files are full, the trace overwrites existing trace data, beginning with the first trace file that was written.

- The maximum size of each trace file is 4 MB.
- Each trace file name begins with jcc.log, and is written into a directory named /Trace.
- If trace files with the same names already exist, the trace data is overwritten.

Although Test.java does not contain any code to do tracing, you want to set the configuration properties so that if the application is modified in the future to do tracing, the settings within the program will take precedence over the settings in the configuration properties. To do that, use the set of configuration properties that begin with db2.jcc.

The configuration property settings look like this:

- db2.jcc.traceFile=jcc.log
- db2.jcc.traceOption=1
- db2.jcc.traceFileSize=4194304
- db2.jcc.traceFileCount=4
- db2.jcc.traceFileAppend=false

You want the trace settings to apply only to your stand-alone program Test.java, so you create a file with these settings, and then refer to the file when you invoke the Java program by specifying the -Ddb2.jcc.propertiesFile option. Suppose that the file that contains the settings is /Test/jcc.properties. To enable tracing when you run Test.java, you issue a command like this:

```
java -Ddb2.jcc.propertiesFile=/Test/jcc.properties Test
```

Suppose that Test.java creates two connections for one `DataSource`. The program does not define a `logWriter` object, so the driver creates a global `logWriter` object for the trace output. During execution of the program, the IBM Data Server Driver for JDBC and SQLJ writes 17 MB of data for the first connection, and 10 MB of data for the second connection.

When the program completes, the following files contain the trace data:

- /Trace/jcc.log_global_0.1
- /Trace/jcc.log_global_0.2
- /Trace/jcc.log_global_0.3
- /Trace/jcc.log_global_0.4
- /Trace/jcc.log_global_1.1
- /Trace/jcc.log_global_1.2
- /Trace/jcc.log_global_1.3

/Trace/jcc.log_global_0.1 contains the last 1 MB of trace data that is written for the first connection, which overwrites the first 1 MB of trace data that was written for that connection.

Related reference

“IBM Data Server Driver for JDBC and SQLJ configuration properties” on page 288

The IBM Data Server Driver for JDBC and SQLJ configuration properties have driver-wide scope.

Example of a trace program under the IBM Data Server Driver for JDBC and SQLJ

You might want to write a single class that includes methods for tracing under the `DriverManager` interface, as well as the `DataSource` interface.

The following example shows such a class. The example uses IBM Data Server Driver for JDBC and SQLJ type 4 connectivity.

Figure 53. Example of tracing under the IBM Data Server Driver for JDBC and SQLJ

```
public class TraceExample
{

  public static void main(String[] args)
  {
    sampleConnectUsingSimpleDataSource();
    sampleConnectWithURLUsingDriverManager();
  }

  private static void sampleConnectUsingSimpleDataSource()
  {
    java.sql.Connection c = null;
    java.io.PrintWriter printWriter =
     new java.io.PrintWriter(System.out, true);
                                       // Prints to console, true means
                                       // auto-flush so you don't lose trace
    try {
      javax.sql.DataSource ds =
       new com.ibm.db2.jcc.DB2SimpleDataSource();
      ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setServerName("sysmvs1.stl.ibm.com");
      ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setPortNumber(5021);
      ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setDatabaseName("san_jose");
      ((com.ibm.db2.jcc.DB2BaseDataSource) ds).setDriverType(4);

     ds.setLogWriter(printWriter);    // This turns on tracing

     // Refine the level of tracing detail
     ((com.ibm.db2.jcc.DB2BaseDataSource) ds).
      setTraceLevel(com.ibm.db2.jcc.DB2SimpleDataSource.TRACE_CONNECTS |
      com.ibm.db2.jcc.DB2SimpleDataSource.TRACE_DRDA_FLOWS);

     // This connection request is traced using trace level
     // TRACE_CONNECTS | TRACE_DRDA_FLOWS
     c = ds.getConnection("myname", "mypass");

     // Change the trace level to TRACE_ALL
     // for all subsequent requests on the connection
     ((com.ibm.db2.jcc.DB2Connection) c).setJccLogWriter(printWriter,
      com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL);
     // The following INSERT is traced using trace level TRACE_ALL
     java.sql.Statement s1 = c.createStatement();
     s1.executeUpdate("INSERT INTO sampleTable(sampleColumn) VALUES(1)");
     s1.close();

     // This code disables all tracing on the connection
     ((com.ibm.db2.jcc.DB2Connection) c).setJccLogWriter(null);

     // The following INSERT statement is not traced
     java.sql.Statement s2 = c.createStatement();
     s2.executeUpdate("INSERT INTO sampleTable(sampleColumn) VALUES(1)");
     s2.close();

     c.close();
    }
    catch(java.sql.SQLException e) {
     com.ibm.db2.jcc.DB2ExceptionFormatter.printTrace(e,
      printWriter, "[TraceExample]");
    }
    finally {
      cleanup(c, printWriter);
      printWriter.flush();
    }
  }
```

```
// If the code ran successfully, the connection should
// already be closed. Check whether the connection is closed.
// If so, just return.
// If a failure occurred, try to roll back and close the connection.

private static void cleanup(java.sql.Connection c,
 java.io.PrintWriter printWriter)
{
  if(c == null) return;

  try {
   if(c.isClosed()) {
      printWriter.println("[TraceExample] " +
       "The connection was successfully closed");
      return;
   }

   // If we get to here, something has gone wrong.
   // Roll back and close the connection.
   printWriter.println("[TraceExample] Rolling back the connection");
   try {
     c.rollback();
   }
   catch(java.sql.SQLException e) {
     printWriter.println("[TraceExample] " +
      "Trapped the following java.sql.SQLException while trying to roll back:");
     com.ibm.db2.jcc.DB2ExceptionFormatter.printTrace(e, printWriter,
      "[TraceExample]");
     printWriter.println("[TraceExample] " +
      "Unable to roll back the connection");
    }
    catch(java.lang.Throwable e) {
      printWriter.println("[TraceExample] Trapped the " +
       "following java.lang.Throwable while trying to roll back:");
      com.ibm.db2.jcc.DB2ExceptionFormatter.printTrace(e,
       printWriter, "[TraceExample]");
      printWriter.println("[TraceExample] Unable to " +
       "roll back the connection");
    }

    // Close the connection
    printWriter.println("[TraceExample] Closing the connection");
    try {
      c.close();
    }
    catch(java.sql.SQLException e) {
      printWriter.println("[TraceExample] Exception while " +
       "trying to close the connection");
      printWriter.println("[TraceExample] Deadlocks could " +
       "occur if the connection is not closed.");
      com.ibm.db2.jcc.DB2ExceptionFormatter.printTrace(e, printWriter,
       "[TraceExample]");
    }
    catch(java.lang.Throwable e) {
      printWriter.println("[TraceExample] Throwable caught " +
       "while trying to close the connection");
      printWriter.println("[TraceExample] Deadlocks could " +
       "occur if the connection is not closed.");
      com.ibm.db2.jcc.DB2ExceptionFormatter.printTrace(e, printWriter,
       "[TraceExample]");
    }
  }
  catch(java.lang.Throwable e) {
    printWriter.println("[TraceExample] Unable to " +
     "force the connection to close");
    printWriter.println("[TraceExample] Deadlocks " +
     "could occur if the connection is not closed.");
    com.ibm.db2.jcc.DB2ExceptionFormatter.printTrace(e, printWriter,
     "[TraceExample]");
  }
}
private static void sampleConnectWithURLUsingDriverManager()
{
  java.sql.Connection c = null;

  // This time, send the printWriter to a file.
  java.io.PrintWriter printWriter = null;
  try {
    printWriter =
      new java.io.PrintWriter(
        new java.io.BufferedOutputStream(
```

```
            new java.io.FileOutputStream("/temp/driverLog.txt"), 4096), true);
    }
    catch(java.io.FileNotFoundException e) {
      java.lang.System.err.println("Unable to establish a print writer for trace");
      java.lang.System.err.flush();
      return;
    }

    try {
      Class.forName("com.ibm.db2.jcc.DB2Driver");
    }
    catch(ClassNotFoundException e) {
      printWriter.println("[TraceExample] " +
       "IBM Data Server Driver for JDBC and SQLJ type 4 connectivity " +
       "is not in the application classpath. Unable to load driver.");
      printWriter.flush();
      return;
    }

    // This URL describes the target data source for Type 4 connectivity.
    // The traceLevel property is established through the URL syntax,
    // and driver tracing is directed to file "/temp/driverLog.txt"
    // The traceLevel property has type int. The constants
    // com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS and
    // com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTS represent
    // int values. Those constants cannot be used directly in the
    // first getConnection parameter. Resolve the constants to their
    // int values by assigning them to a variable. Then use the
    // variable as the first parameter of the getConnection method.
    String databaseURL =
     "jdbc:db2://sysmvs1.stl.ibm.com:5021" +
     "/sample:traceFile=/temp/driverLog.txt;traceLevel=" +
     (com.ibm.db2.jcc.DB2BaseDataSource.TRACE_DRDA_FLOWS |
     com.ibm.db2.jcc.DB2BaseDataSource.TRACE_CONNECTS) + ";";

    // Set other properties
    java.util.Properties properties = new java.util.Properties();
    properties.setProperty("user", "myname");
    properties.setProperty("password", "mypass");

    try {
     // This connection request is traced using trace level
     // TRACE_CONNECTS | TRACE_DRDA_FLOWS
     c = java.sql.DriverManager.getConnection(databaseURL, properties);

     // Change the trace level for all subsequent requests
     // on the connection to TRACE_ALL
     ((com.ibm.db2.jcc.DB2Connection) c).setJccLogWriter(printWriter,
      com.ibm.db2.jcc.DB2BaseDataSource.TRACE_ALL);

     // The following INSERT is traced using trace level TRACE_ALL
     java.sql.Statement s1 = c.createStatement();
     s1.executeUpdate("INSERT INTO sampleTable(sampleColumn) VALUES(1)");
     s1.close();

     // Disable all tracing on the connection
     ((com.ibm.db2.jcc.DB2Connection) c).setJccLogWriter(null);

      // The following SQL insert code is not traced
      java.sql.Statement s2 = c.createStatement();
      s2.executeUpdate("insert into sampleTable(sampleColumn) values(1)");
      s2.close();

      c.close();
    }
    catch(java.sql.SQLException e) {
     com.ibm.db2.jcc.DB2ExceptionFormatter.printTrace(e, printWriter,
      "[TraceExample]");
    }
    finally {
      cleanup(c, printWriter);
      printWriter.flush();
    }
  }
}
```

Techniques for monitoring IBM Data Server Driver for JDBC and SQLJ sysplex support

To monitor IBM Data Server Driver for JDBC and SQLJ sysplex support, you need to monitor the global transport objects pool.

You can monitor the global transport objects pool in either of the following ways:

- Using traces that you start by setting IBM Data Server Driver for JDBC and SQLJ configuration properties
- Using an application programming interface

Configuration properties for monitoring the global transport objects pool

The db2.jcc.dumpPool, db2.jcc.dumpPoolStatisticsOnSchedule, and db2.jcc.dumpPoolStatisticsOnScheduleFile configuration properties control tracing of the global transport objects pool.

Example: The following set of configuration property settings cause error messages, dump pool error messages, and transport pool statistics to be written every 60 seconds to a file named /home/WAS/logs/srv1/poolstats:

```
db2.jcc.dumpPool=DUMP_SYSPLEX_MSG|DUMP_POOL_ERROR
db2.jcc.dumpPoolStatisticsOnSchedule=60
db2.jcc.dumpPoolStatisticsOnScheduleFile=/home/WAS/logs/srv1/poolstats
```

An entry in the pool statistics file looks like this:

```
time Scheduled PoolStatistics npr:2575 nsr:2575 lwroc:439 hwroc:1764 coc:372
aooc:362 rmoc:362 nbr:2872 tbt:857520 tpo:10
group: DSNDB port: 446 hwmpo: 20 twte: 5 ngipr: 50 ttcpto: 2
   member: port: 446 DB1A hwmiut: 6 hwmt: 2 tmct: 1 trto: 0
   member: port: 446 DB1B hwmiut: 7 hwmt: 2 tmct: 1 trto: 0
   member: port: 446 DB1C hwmiut: 6 hwmt: 1 tmct: 0 trto: 1
```

The meanings of the fields are:

npr
The total number of requests that the IBM Data Server Driver for JDBC and SQLJ has made to the pool since the pool was created.

nsr
The number of successful requests that the IBM Data Server Driver for JDBC and SQLJ has made to the pool since the pool was created. A successful request means that the pool returned an object.

lwroc
The number of objects that were reused but were not in the pool. This can happen if a Connection object releases a transport object at a transaction boundary. If the Connection object needs a transport object later, and the original transport object has not been used by any other Connection object, the Connection object can use that transport object.

hwroc
The number of objects that were reused from the pool.

coc
The number of objects that the IBM Data Server Driver for JDBC and SQLJ created since the pool was created.

aooc
The number of objects that exceeded the idle time that was specified by db2.jcc.maxTransportObjectIdleTime and were deleted from the pool.

rmoc
The number of objects that have been deleted from the pool since the pool was created.

nbr
The number of requests that the IBM Data Server Driver for JDBC and SQLJ made to the pool that the pool blocked because the pool reached its maximum capacity. A blocked request might be successful if an object is returned to the pool before the db2.jcc.maxTransportObjectWaitTime is exceeded and an exception is thrown.

tbt
The total time in milliseconds for requests that were blocked by the pool. This time can be much larger than the elapsed execution time of the application if the application uses multiple threads.

sbt
The shortest time in milliseconds that a thread waited to get a transport object from the pool. If the time is under one millisecond, the value in this field is zero.

lbt
The longest time in milliseconds that a thread waited to get a transport object from the pool.

abt
The average amount of time in milliseconds that threads waited to get a transport object from the pool. This value is tbt/nbr.

tpo
The number of objects that are currently in the pool.

group
The data sharing group for which transport pool statistics were gathered.

port
The port number of the data sharing group or member.

hwmpo
The maximum number of pool objects that were created since the pool was created.

twte
The number of times that the maxTransportWaitTime value was exceeded since the pool was created.

ngipr
The number of times that the group IP address was used since the pool was created.

ttcpto
The total number of times that members of the data sharing group had a connection timeout when they were establishing a new connection.

member
The member of the data sharing group for which transport statistics were gathered.

hwmiut
The maximum number of in-use transports for the data sharing member since the pool was created.

hwmt
The maximum number of transports that have been allocated to the data sharing member since the pool was created.

tmct
The number of times that the memberConnectTimeout value was reached for the data sharing member since the pool was created.

trto
The number of times that a read timeout occurred for the data sharing member since the pool was created.

Application programming interfaces for monitoring the global transport objects pool

You can write applications to gather statistics on the global transport objects pool. Those applications create objects in the `DB2PoolMonitor` class and invoke methods to retrieve information about the pool.

For example, the following code creates an object for monitoring the global transport objects pool:

```
import com.ibm.db2.jcc.DB2PoolMonitor;
DB2PoolMonitor transportObjectPoolMonitor =
        DB2PoolMonitor.getPoolMonitor (DB2PoolMonitor.TRANSPORT_OBJECT);
```

After you create the DB2PoolMonitor object, you can use methods in the DB2PoolMonitor class to monitor the pool.

Chapter 19. Tracing IBM Data Server Driver for JDBC and SQLJ C/C++ native driver code

To debug applications that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, you might need to trace the C/C++ native driver code.

Procedure

To collect, format, and print the trace data for the C/C++ native driver code, follow these steps:

1. Enable tracing of C/C++ native driver code by setting a value for the db2.jcc.t2zosTraceFile global configuration property.

   That value is the name of the file to which the IBM Data Server Driver for JDBC and SQLJ writes the trace data.
2. Run the db2jcctrace command from the z/OS UNIX System Services command line.

   By default, the trace data goes to stdout. You can pipe the data to another file.

Example

Suppose that db2.jcc.t2zosTraceFile has this setting:

```
db2.jcc.t2zosTraceFile=/SYSTEM/tmp/jdbctraceNative
```

Execute this command to format all available trace data for the C/C++ native driver code, and send the output to stdout:

```
db2jcctrace format flow /SYSTEM/tmp/jdbctraceNative
```

Related concepts

"Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties" on page 536
The IBM Data Server Driver for JDBC and SQLJ configuration properties let you set property values that have driver-wide scope. Those settings apply across applications and `DataSource` instances. You can change the settings without having to change application source code or `DataSource` characteristics.

Related reference

"db2jcctrace - Format IBM Data Server Driver for JDBC and SQLJ trace data for C/C++ native driver code" on page 643
db2jcctrace writes formatted trace data for traces of C/C++ native driver code under IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

db2jcctrace - Format IBM Data Server Driver for JDBC and SQLJ trace data for C/C++ native driver code

db2jcctrace writes formatted trace data for traces of C/C++ native driver code under IBM Data Server Driver for JDBC and SQLJ type 2 connectivity.

By default, the trace data is written to stdout. You can pipe the output to any file.

db2jcctrace syntax



Notes:

© Copyright IBM Corp. 1998, 2017

[1] You must specify one of these parameters.

db2jcctrace parameters

format
Specifies that the output trace file contains formatted trace data.

Abbreviation: `fmt`

flow
Specifies that the output trace file contains control flow information.

Abbreviation: `flw`

information
Specifies that the output trace file contains information about the trace, such as the version of the driver, the time at which the trace was taken, and whether the trace file wrapped or was truncated. This information is also included in the output trace file when you specify format or flow.

Abbreviation: `inf` or `info`

input-file-name
Specifies the name of the file from which `db2jcctrace` is to read the unformatted trace data. *input-file-name* is the same as the value of the db2.jcc.t2zosTraceFile global configuration parameter.

Related concepts
“Customization of IBM Data Server Driver for JDBC and SQLJ configuration properties” on page 536
The IBM Data Server Driver for JDBC and SQLJ configuration properties let you set property values that have driver-wide scope. Those settings apply across applications and `DataSource` instances. You can change the settings without having to change application source code or `DataSource` characteristics.

Related tasks
“Tracing IBM Data Server Driver for JDBC and SQLJ C/C++ native driver code” on page 643
To debug applications that use IBM Data Server Driver for JDBC and SQLJ type 2 connectivity on Db2 for z/OS, you might need to trace the C/C++ native driver code.

Chapter 20. System monitoring for the IBM Data Server Driver for JDBC and SQLJ

To assist you in monitoring the performance of your applications with the IBM Data Server Driver for JDBC and SQLJ, the driver provides two methods to collect information for a connection.

That information is:

Core driver time
The sum of elapsed monitored API times that were collected while system monitoring was enabled, in microseconds. In general, only APIs that might result in network I/O or database server interaction are monitored.

Network I/O time
The sum of elapsed network I/O times that were collected while system monitoring was enabled, in microseconds.

Server time
The sum of all reported database server elapsed times that were collected while system monitoring was enabled, in microseconds.

Application time
The sum of the application, JDBC driver, network I/O, and database server elapsed times, in milliseconds.

The two methods are:

- The `DB2SystemMonitor` interface
- The TRACE_SYSTEM_MONITOR trace level

To collect system monitoring data using the `DB2SystemMonitor` interface: Perform these basic steps:

1. Invoke the `DB2Connection.getDB2SystemMonitor` method to create a `DB2SystemMonitor` object.
2. Invoke the `DB2SystemMonitor.enable` method to enable the `DB2SystemMonitor` object for the connection.
3. Invoke the `DB2SystemMonitor.start` method to start system monitoring.
4. When the activity that is to be monitored is complete, invoke `DB2SystemMonitor.stop` to stop system monitoring.
5. Invoke the `DB2SystemMonitor.getCoreDriverTimeMicros`, `DB2SystemMonitor.getNetworkIOTimeMicros`, `DB2SystemMonitor.getServerTimeMicros`, or `DB2SystemMonitor.getApplicationTimeMillis` methods to retrieve the elapsed time data.

   The server time that is returned by `DB2SystemMonitor.getServerTimeMicros` does not include commit or rollback time.

For example, the following code demonstrates how to collect each type of elapsed time data. The numbers to the right of selected statements correspond to the previously described steps.

© Copyright IBM Corp. 1998, 2017

```
import java.sql.*;
import com.ibm.db2.jcc.*;
public class TestSystemMonitor
{
  public static void main(String[] args)
  {
    String url = "jdbc:db2://sysmvs1.svl.ibm.com:5021/san_jose";
    String user="db2adm";
    String password="db2adm";
    try
    {
      // Load the IBM Data Server Driver for JDBC and SQLJ
      Class.forName("com.ibm.db2.jcc.DB2Driver");
      System.out.println("**** Loaded the JDBC driver");

      // Create the connection using the IBM Data Server Driver for JDBC and SQLJ
      Connection conn = DriverManager.getConnection
(url,user,password);
      // Commit changes manually
      conn.setAutoCommit(false);
      System.out.println("**** Created a JDBC connection to the data source");
      DB2SystemMonitor systemMonitor =                                    1
        ((DB2Connection)conn).getDB2SystemMonitor();
      systemMonitor.enable(true);                                         2
      systemMonitor.start(DB2SystemMonitor.RESET_TIMES);                  3
      Statement stmt = conn.createStatement();
      int numUpd = stmt.executeUpdate(
        "UPDATE EMPLOYEE SET PHONENO='4657' WHERE EMPNO='000010'");
      systemMonitor.stop();                                               4
      System.out.println("Server elapsed time (microseconds)="
        + systemMonitor.getServerTimeMicros());                           5
      System.out.println("Network I/O elapsed time (microseconds)="
        + systemMonitor.getNetworkIOTimeMicros());
      System.out.println("Core driver elapsed time (microseconds)="
        + systemMonitor.getCoreDriverTimeMicros());
      System.out.println("Application elapsed time (milliseconds)="
        + systemMonitor.getApplicationTimeMillis());
      conn.rollback();
      stmt.close();
      conn.close();
    }
    // Handle errors
    catch(ClassNotFoundException e)
    {
      System.err.println("Unable to load the driver, " + e);
    }
    catch(SQLException e)
    {
      System.out.println("SQLException: " + e);
      e.printStackTrace();
    }
  }
}
```

Figure 54. Example of using DB2SystemMonitor methods to collect system monitoring data

To collect system monitoring information using the trace method: Start a JDBC trace, using configuration properties or `Connection` or `DataSource` properties. Include TRACE_SYSTEM_MONITOR when you set the traceLevel property. For example:

```
String url = "jdbc:db2://sysmvs1.stl.ibm.com:5021/san_jose" +
 ":traceFile=/u/db2p/jcctrace;" +
 "traceLevel=" + com.ibm.db2.jcc.DB2BaseDataSource.TRACE_SYSTEM_MONITOR + ";";
```

The trace records with system monitor information look similar to this:

```
[jcc][SystemMonitor:start]
…
[jcc][SystemMonitor:stop] core: 565.67ms | network: 211.695ms | server: 207.771ms
```

Information resources for Db2 12 for z/OS and related products

Information about Db2 12 for z/OS and products that you might use in conjunction with Db2 12 is available online in IBM Documentation.

You can find the complete set of product documentation for Db2 12 for z/OS in IBM Documentation.

You can also download other PDF format manuals for Db2 12 for z/OS from IBM Documentation in PDF format manuals for Db2 12 for z/OS (Db2 for z/OS in IBM Documentation).

© Copyright IBM Corp. 1998, 2017

Notices

This information was developed for products and services offered in the US. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785 US

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Director of Licensing IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785 US

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

© Copyright IBM Corp. 1998, 2017

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as shown below:

© (*your company name*) (*year*).
Portions of this code are derived from IBM Corp. Sample Programs.
© Copyright IBM Corp. (*enter the year or years*).

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Programming interface information

This information is intended to help you write applications that use Java to access Db2 12 for z/OS servers. This book primarily documents General-use Programming Interface and Associated Guidance Information provided by Db2 12 for z/OS.

General-use Programming Interface and Associated Guidance Information

General-use Programming Interfaces allow the customer to write programs that obtain the services of Db2 12 for z/OS.

Trademarks

IBM, the IBM logo, and ibm.com® are trademarks or registered marks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at: http://www.ibm.com/legal/copytrade.shtml.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Privacy policy considerations

IBM Software products, including software as a service solutions, (“Software Offerings”) may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering’s use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at http://www.ibm.com/privacy and IBM's Online Privacy Statement at http://www.ibm.com/privacy/details the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at http://www.ibm.com/software/info/product-privacy.

Glossary

The glossary is available in IBM Knowledge Center.

See the Glossary topic for definitions of Db2 for z/OS terms.

© Copyright IBM Corp. 1998, 2017

Index

Special Characters

-Infinity
  retrieving in Java applications 220

A

accessibility
  keyboard xii
  shortcut keys xii
ALLOW DEBUG MODE
  CREATE PROCEDURE parameter 186
alternate groups
  Db2 on Linux, UNIX, and Windows systems 600
application compatibility
  Db2 for z/OS 555
application development
  high availability
    direct connections to Db2 for z/OS servers 616
  JDBC
    application programming 9
  SQLJ 119
application programming for high availability
  connections to Db2 on Linux, UNIX, and Windows systems 604
ARRAY parameters
  invoking stored procedures from JDBC programs 70
assignment-clause
  SQLJ 362
auto-generated keys
  retrieving for DELETE, JDBC application 75
  retrieving for INSERT, JDBC application 73
  retrieving for MERGE, JDBC application 75
  retrieving for UPDATE, JDBC application 75
  retrieving in JDBC application 73
autocommit modes
  default JDBC 108
automatic client reroute
  client applications 589
  Db2 for z/OS 615
automatic client reroute support, client operation 597
automatically generated keys
  retrieving
    DELETE statement, JDBC application 75
    INSERT statement, JDBC application 73
    JDBC applications 73
    MERGE statement, JDBC application 75
    UPDATE statement, JDBC application 75

B

batch queries
  JDBC 40
batch updates
  JDBC 33
  SQLJ 138
BatchUpdateException exception
  retrieving information 115
binary XML format
  Java applications 98
binding SQLJ applications
  accessing multiple servers 198

C

CallableStatement class 51
client affinities
  .NET 605
  CLI 605
  IBM Data Server Driver for JDBC and SQLJ 605
client affinities, example of enabling
  Java clients 606
client application
  automatic client reroute 589
  high availability 589
  transaction-level load balancing 589
client authentication
  IBM Data Server Driver for JDBC and SQLJ 585
client configuration, automatic client reroute support
  Db2 on Linux, UNIX, and Windows systems 591
client configuration, sysplex workload balancing
  Db2 for z/OS 610
client configuration, workload balancing support
  Db2 on Linux, UNIX, and Windows systems 594
client info properties
  IBM Data Server Driver for JDBC and SQLJ 83, 84
clients
  alternate groups
    connections to Db2 on Linux, UNIX, and Windows systems 600
  automatic client reroute
    connections to Db2 for z/OS 615
commands
  db2sqljbind 526
  db2sqljprint 530
  sqlj 512
  SQLJ 512
comments
  JDBC applications 29
  SQLJ applications 132
commits
  SQLJ transactions 171
  transactions
    JDBC 107
configuration
  JDBC 536
  SQLJ 536
configuration properties
  customizing 536
  details 288
  parameters 536
configuring

configuring *(continued)*
Java Runtime Environment 582
connection context
class 121
closing 173
default 121
object 121
connection declaration clause
SQLJ 355
connection pooling
overview 619
connections
closing
importance 117, 173
data sources using SQLJ 121
DataSource interface 20
existing 126
context clause
SQLJ 358, 359

D

data
retrieving
JDBC 38
data server connection
testing with DB2Jcc 629
data sources
connecting to
DriverManager 13
JDBC 11
JDBC DataSource 20
data type mappings
Java types to other types 207
database manager versions
associated driver versions 4
DatabaseMetaData methods 25
DataSource interface
SQLJ
connection technique 3 124
connection technique 4 125
DataSource objects
creating 23
deploying 23
date value adjustment
JDBC applications 215
SQLJ applications 215
Db2 for z/OS
binding packages 516
client configuration, sysplex workload balancing 610
direct connections 614, 616
server access from Java programs 560
sysplex support
overview 608
DB2 on Linux, UNIX, and Windows levels
associated Java driver versions 6
Db2 on Linux, UNIX, and Windows systems
client configuration, automatic client reroute support 591
client configuration, workload balancing support 594
high-availability support 590
Db2 on Linux, UNIX, and Windows systems high availability support, example of enabling
IBM Data Server Driver for JDBC and SQLJ 593
Db2 on Linux, UNIX, and Windows systems workload balancing support, example of enabling
IBM Data Server Driver for JDBC and SQLJ 596
Db2 on Linux, UNIX, and Windows systems, connections
application programming for high availability 604
DB2Binder class 401
DB2Binder utility 539
DB2BlobFileReference class 402
DB2CallableStatement interface 402
DB2ClientRerouteServerList class 409
DB2ClobFileReference class 410
DB2Connection interface 410
DB2Connection.zLoad method
loading a Db2 for z/OS table 105
DB2ConnectionPool class 429
DB2ConnectionPoolDataSource class 433
DB2DatabaseMetaData interface 435
DB2DatabaseMetaData methods 28
DB2DataSource class 437
DB2Diagnosable class
retrieving the SQLCA 172
DB2Diagnosable interface 436
DB2Driver class 438
DB2ExceptionFormatter class 439
DB2FileReference class 439
DB2Jcc utility
details 632
testing a data server connection 629
DB2JCCPlugin interface 440
db2jcctrace command 643
DB2JSONResultSet interface 441
DB2LobTableCreator utility 547
DB2ParameterMetaData interface 442
DB2PooledConnection interface 443
DB2PoolMonitor class 445
DB2PreparedStatement interface 448
DB2ResultSet interface 462
DB2ResultSetMetaData interface 466
DB2RowID interface 467
DB2SimpleDataSource class
definition 23
details 468
DB2Sqlca class 468
db2sqljbind command 526
db2sqljcustomize command 516
db2sqljprint
formation JCC customized profile 631
db2sqljprint command
details 530
formatting information about SQLJ customized profile 629
DB2Statement interface 469
DB2SystemMonitor interface 472
DB2TraceManager class 475
DB2TraceManagerMXBean interface 478
DB2Types class 481
DB2Version class 482
DB2XADataSource class 483
DB2Xml interface 485
DB2XmlAsBlobFileReference class 487
DB2XmlAsClobFileReference class 488
DBBatchUpdateException interface 391
DBINFO

DBINFO *(continued)*
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186
DBTimestamp class 488
DBTimestamp object
IBM Data Server Driver for JDBC and SQLJ 63
default connection context 127
deregisterDB2XMLObject method 99
disability xii
DISABLE DEBUG MODE
CREATE PROCEDURE parameter 186
DISALLOW DEBUG MODE
CREATE PROCEDURE parameter 186
distinct types
JDBC applications 70
SQLJ applications 162
distributed transactions
example 623
IBM Data Server Driver for JDBC and SQLJ type 4 connectivity 623
driver versions
associated database manager versions 4
DriverManager interface
SQLJ
SQLJ connection technique 1 121
SQLJ connection technique 2 122
drivers
determining IBM Data Server Driver for JDBC and SQLJ version 4
dynamic data format 153

E

enabling
IBM Data Server Driver for JDBC and SQLJ support routines 537
encryption
IBM Data Server Driver for JDBC and SQLJ 569
environment
Java stored procedures 177
Java user-defined functions 177
environment variables
IBM Data Server Driver for JDBC and SQLJ 534
JDBC 536
settings for Java routine 180
SQLJ 536
z/OS Application Connectivity to Db2 for z/OS feature 553
errors
SQLJ 172
escape syntax
IBM Data Server Driver for JDBC and SQLJ 350
examples
deregisterDB2XMLObject 99
registerDB2XMLSchema 99
exceptions
IBM Data Server Driver for JDBC and SQLJ 108
executable clause 357
executeUpdate methods 33
extended client information
DB2PreparedStatement constants 88, 89
DB2PreparedStatement methods 88
DB2ResultSet methods 89
extended parameter information
extended parameter information *(continued)*
IBM Data Server Driver for JDBC and SQLJ 87
EXTERNAL
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186

F

failover
IBM Data Server Driver for JDBC and SQLJ type 2 connectivity 617
FINAL CALL
CREATE FUNCTION parameter 186

G

general-use programming information, described 650
getCause method 108
getDatabaseProductName method 26
getDatabaseProductVersion method 26
global transactions
JDBC and SQLJ 627

H

high availability
client application 589
high-availability support
Db2 on Linux, UNIX, and Windows systems 590
host expressions
SQLJ 128, 129, 351

I

IBM data server clients
alternate groups
Db2 on Linux, UNIX, and Windows systems 600
automatic client reroute
Db2 for z/OS 615
IBM Data Server Driver for JDBC and SQLJ
client info properties 83
connecting to data sources 13
connection concentrator monitoring 640
Db2 for z/OS 560
diagnostic utility 632
errors 503
example of enabling Db2 on Linux, UNIX, and Windows systems high availability support 593
example of enabling Db2 on Linux, UNIX, and Windows systems workload balancing support 596
example of enabling sysplex workload balancing 612
exceptions 108
extended client information 82
installing 557
installing with DB2 533
JDBC extensions 388
Kerberos security 571, 575
LOB support
JDBC 56, 58
SQLJ 153
properties 223
security
details 563

IBM Data Server Driver for JDBC and SQLJ *(continued)*
security *(continued)*
encrypted password 569
encrypted user ID 569
user ID and password 565
user ID-only 568
SQL escape syntax 350
SQLExceptions 111
SQLSTATEs 510
trace program example 637
tracing with configuration parameters example 635
trusted context support 577
type 2 connectivity
Db2 for z/OS failover support 617
overview 22
type 4 connectivity 22
upgrading to a new version 550
version determination 4
warnings 108
XML support 163
IBM Data Server Driver for JDBC and SQLJ versions
DB2 levels 6
IBM Data Server Driver for JDBC and SQLJ-only fields
DB2Types class 481
IBM Data Server Driver for JDBC and SQLJ-only methods
DB2BaseDataSource class 391
DB2Binder class 401
DB2BlobFileReference class 402
DB2CallableStatement interface 402
DB2ClientRerouteServerList class 409
DB2ClobFileReference class 410
DB2Connection interface 410
DB2ConnectionPool class 429
DB2ConnectionPoolDataSource class 433
DB2DatabaseMetaData interface 435
DB2DataSource class 437
DB2Diagnosable interface 436
DB2Driver class 438
DB2ExceptionFormatter class 439
DB2FileReference class 439
DB2JCCPlugin interface 440
DB2ParameterMetaData interface 442
DB2PooledConnection interface 443
DB2PoolMonitor class 445
DB2PreparedStatement interface 448
DB2ResultSet interface 462
DB2ResultSetMetaData interface 466
DB2RowID interface 467
DB2SimpleDataSource class 468
DB2sqlca class 468
DB2Statement interface 469
DB2SystemMonitor interface 472
DB2TraceManager class 475
DB2TraceManagerMXBean interface 478
DB2Version class 482
DB2XADataSource class 483
DB2Xml interface 485
DB2XmlAsBlobFileReference class 487
DB2XmlAsClobFileReference class 488
DBBatchUpdateException interface 391
DBTimestamp class 488
JSON interface 441
LoadResult class 490
IBM Data Server Driver for JDBC and SQLJ-only properties
DB2BaseDataSource class 391
DB2ClientRerouteServerList class 409
DB2ConnectionPool class 429
DB2ConnectionPoolDataSource class 433
DB2SimpleDataSource class 468
IBM data server drivers
alternate groups
Db2 on Linux, UNIX, and Windows systems 600
automatic client reroute
Db2 for z/OS 615
implements clause
SQLJ 352
Infinity
retrieving in Java applications 220
installation
IBM Data Server Driver for JDBC and SQLJ 557
installing
Java driver 533
installing IBM Data Server Driver for JDBC and SQLJ
with DB2 533
internal statement cache
IBM Data Server Driver for JDBC and SQLJ 621
isolation levels
JDBC 106
SQLJ 171
iterator conversion clause
SQLJ 363
iterator declaration clause
SQLJ 356
iterators
obtaining JDBC result sets from 156
positioned DELETE 133
positioned UPDATE 133

J

JAR files
creating for JDBC routines 205
defining to DB2 186, 190
Java
applications
accessing z/OS servers 560
overview 1
environment
customization 536
Java driver
installing 533
Java programs
preparing and running 197
Java routines
environment variable settings 180
moving to a 64-bit environment 184
preparing 200
testing 194
WLM environment 178
Java routines with no SQLJ
preparing 200, 202
program preparation 200, 201
Java routines with SQLJ
program preparation 202, 204
Java stored procedures
defining to DB2 186

Java stored procedures *(continued)*
differences from Java programs 191
differences from other stored procedures 191
parameters specific to 186
WLM environment definitions 538
writing 191
Java user-defined functions
defining to DB2 186
differences from Java program 191
differences from other user-defined functions 191
parameters specific to 186
writing 191
JAVAENV data set
characteristics 180
JDBC
4.0
getColumnLabel change 501
getColumnName change 501
accessing packages 25
APIs 318
applications
24 as hour value 215
data retrieval 38
example 9
invalid Gregorian date 215
programming overview 9
transaction control 106
variables 28
batch errors 115
batch queries 40
batch updates 33
comments 29
configuring 536
connections 23
data type mappings 207
Db2 for z/OS servers 560
drivers
details 3
differences 491
environment variables 536
executeUpdate methods 33
executing SQL 30
extensions 388
file reference variables 103
IBM Data Server Driver for JDBC and SQLJ installation 557
input file reference variables 103
isolation levels 106
named parameter markers 76–78
objects
creating 30
modifying 30
problem diagnosis 629
program preparation 197
ResultSet holdability 44
ResultSets
delete holes 49
holdability 42
inserting row 50, 51
running programs 206
sample program 548
scrollable ResultSet 42, 44
SQLWarning 113
transactions
JDBC *(continued)*
transactions *(continued)*
committing 107
default autocommit modes 108
rolling back 107
updatable ResultSet 42, 44
JSON interface
ResultSet objects to JSON documents 79

K

Kerberos authentication protocol
IBM Data Server Driver for JDBC and SQLJ 571, 575

L

LANGUAGE
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186
large objects (LOBs)
compatible Java data types
JDBC applications 59
SQLJ applications 154
IBM Data Server Driver for JDBC and SQLJ 56, 58, 153
locators
IBM Data Server Driver for JDBC and SQLJ 57, 58
SQLJ 153
Load
zLoad method 105
loading libraries
IBM Data Server Driver for JDBC and SQLJ 534
LoadResult class 490

M

memory
IBM Data Server Driver for JDBC and SQLJ 116
monitoring
system
IBM Data Server Driver for JDBC and SQLJ 645
multi-row operations 47
multiple result sets
retrieving from stored procedure in JDBC application
keeping result sets open 55
known number 53
overview 53
unknown number 54
retrieving from stored procedure in SQLJ application 152

N

named iterators
passed as variables 137
result set iterator 143
named parameter markers
CallableStatement objects 78
JDBC 76
PreparedStatement objects 77
NaN
retrieving in Java applications 220
NO SQL
CREATE FUNCTION parameter 186

NO SQL *(continued)*
CREATE PROCEDURE parameter 186

P

packages
JDBC 25
SQLJ 127
PARAMETER STYLE
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186
ParameterMetaData methods 37
positioned deletes
SQLJ 133
positioned iterators
passed as variables 137
result set iterators 144
positioned updates
SQLJ 133
PreparedStatement methods
SQL statements with no parameter markers 31
SQL statements with parameter markers 31, 39
problem determination
JDBC 629
SQLJ 629
program preparation
example, Java routine with SQLJ 202
Java routines with no SQLJ 200, 201
Java routines with SQLJ 202, 204
JDBC programs 197
PROGRAM TYPE
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186
programming interface information, described 650
progressive streaming
IBM Data Server Driver for JDBC and SQLJ 56, 58
JDBC 153
properties
IBM Data Server Driver for JDBC and SQLJ
customizing 536
for all database products 224
for Db2 for z/OS 274
for Db2 on Linux, UNIX, and Windows systems 268–270
for Db2 servers 253
for IBM Informix 268, 269, 284
overview 223

R

RACF key ring 581
reference information
Java 207
registerDB2XMLSchema method 99
resources
releasing
closing connections 117, 173
restrictions
SQLJ variable names 128, 129
result set iterator
public declaration in separate file 156
result set iterators
details 142
result set iterators *(continued)*
generating JDBC ResultSets from SQLJ iterators 156
named 143
positioned 144
retrieving data from JDBC result sets using SQLJ iterators 156
ResultSet
holdability 42
inserting row 50
testing for delete hole 49
testing for inserted row 51
ResultSet holdability
JDBC 44
ResultSet objects
converting to JSON documents 79
ResultSetMetaData methods
ResultSetMetaData.getColumnLabel change in value 501
ResultSetMetaData.getColumnName change in value 501
retrieving result set information 41
retrieving data
JDBC
data source information 25, 28
PreparedStatement.executeQuery method 39
result set information 41
tables 38
SQLJ 142, 146, 147
retrieving parameter information
JDBC 37
retrieving SQLCA
DB2Diagnosable class 172
return codes
IBM Data Server Driver for JDBC and SQLJ errors 503
rollbacks
JDBC transactions 107
SQLJ transactions 171
routines
invoking
XML parameters in Java applications 96
ROWID 159
RUN OPTIONS
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186
running programs
SQLJ and JDBC 206

S

sample program
JDBC 548
savepoints
JDBC applications 71
SQLJ applications 162
SCRATCHPAD
CREATE FUNCTION parameter 186
scrollable iterators
SQLJ 148
scrollable ResultSet
JDBC 44
scrollable ResultSets
JDBC 42
SDKs
version 1.5 168

security
IBM Data Server Driver for JDBC and SQLJ
encrypted security-sensitive data 569
encrypted user ID or encrypted password 569
Kerberos 571, 575
security mechanisms 563
user ID and password 565
user ID only 568
SQLJ program preparation 587
SECURITY
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186
SET TRANSACTION clause 362
shortcut keys
keyboard xii
SQL statements
error handling
SQLJ applications 172
executing
JDBC interfaces 30
SQLJ applications 132, 158
SQLException
IBM Data Server Driver for JDBC and SQLJ 111
SQLJ
accessing packages for 127
applications
24 as hour value 215
examples 119
invalid Gregorian date 215
programming 119
transaction control 171
assignment clause 362
batch updates 138
binding applications to access multiple servers 198
calling stored procedures 152
clauses 350
collecting trace data 629
comments 132
connecting to data source 121
connecting using default context 127
connection declaration clause 355
context clause 358, 359
DataSource interface 124, 125
Db2 tables
creating 133
modifying 133
DriverManager interface 121, 122
drivers 3
environment variables 536
error handling 172
executable clauses 357
executing SQL 132
execution context 158
execution control 158
existing connections 126
file reference variables 167
host expressions 128, 129, 351
implements clause 352
input file reference variables 167
installing runtime environment 536
isolation levels 171
iterator conversion clause 363
iterator declaration clause 356
multiple instances of iterator 147
SQLJ *(continued)*
multiple iterators on table 146
problem diagnosis 629
Profile Binder command 526
Profile Printer command 530
program preparation 512
result set iterator 142
retrieving SQLCA 172
running programs 206
scrollable iterators 148
SDK for Java Version 5 functions 168
security 587
SET TRANSACTION clause 362
SQLWarning 173
statement reference 350
transactions 171
translator command 512
variable names 128, 129
with-clause 353
sqlj command 512
SQLJ programs
preparing 197
SQLJ variable names
restrictions 128, 129
sqlj.runtime package 364
sqlj.runtime.AsciiStream 375, 385
sqlj.runtime.BinaryStream 376
sqlj.runtime.CharacterStream 376
sqlj.runtime.ConnectionContext 365
sqlj.runtime.ExecutionContext 377
sqlj.runtime.ForUpdate 369
sqlj.runtime.NamedIterator 369
sqlj.runtime.PositionedIterator 370
sqlj.runtime.ResultSetIterator 370
sqlj.runtime.Scrollable 373
sqlj.runtime.SQLNullException 385
sqlj.runtime.UnicodeStream 387
SQLSTATE
IBM Data Server Driver for JDBC and SQLJ errors 510
SQLWarning
IBM Data Server Driver for JDBC and SQLJ 113
SQLJ applications 173
SSID
IBM Data Server Driver for JDBC and SQLJ 288
SSL
IBM Data Server Driver for JDBC and SQLJ 579
sslConnection property 580
sslConnection property 580
statement caching
IBM Data Server Driver for JDBC and SQLJ 621
Statement.executeQuery 38
static and non-final variables
Java routines 192
stored procedures
calling
CallableStatement class 51
JDBC applications 70
SQLJ applications 152
Db2 for z/OS 51
Java 177
keeping result sets open in JDBC applications 55
retrieving result sets
known number (JDBC) 53
multiple (JDBC) 53

stored procedures *(continued)*
retrieving result sets *(continued)*
multiple (SQLJ) 152
unknown number (JDBC) 54
returning result sets 193
stored procedures for IBM Data Server Driver support
creating 539
syntax diagram
how to read xiii
sysplex
direct connections to Db2 for z/OS 614
support 608
sysplex support, example of enabling
IBM Data Server Driver for JDBC and SQLJ 612

T

testing
Java routines 194
time stamps
data loss avoidance
JDBC applications 219
SQLJ applications 219
time value adjustment
JDBC applications 215
SQLJ applications 215
TIMESTAMP data type
data loss
JDBC applications 219
SQLJ applications 219
TIMESTAMP WITH TIME ZONE
IBM Data Server Driver for JDBC and SQLJ 63, 160
timestamps with time zones
setting TIMESTAMP WITH TIME ZONE columns 222
token authentication
IBM Data Server Driver for JDBC and SQLJ 586
trace C/C++ native driver
code
db2jcctrace 643
traces
IBM Data Server Driver for JDBC and SQLJ 629, 635, 637
transaction control
JDBC 106
SQLJ 171
transaction-level load balancing
client application 589
trusted contexts
JDBC support 577

U

updatable ResultSet
inserting row 50
JDBC 42, 44
testing for delete hole 49
testing for inserted row 51
updates
data
PreparedStatement.executeUpdate method 31
URL format
DB2BaseDataSource class 14, 17
user ID and password security
IBM Data Server Driver for JDBC and SQLJ 565
user ID-only security
IBM Data Server Driver for JDBC and SQLJ 568
user-defined functions
access to z/OS UNIX System Services 186
Java 177

W

warnings
IBM Data Server Driver for JDBC and SQLJ 108
with clause
SQLJ 353
WLM ENVIRONMENT
CREATE FUNCTION parameter 186
CREATE PROCEDURE parameter 186
WLM environments
defining for Java stored procedures 538
values for Java routines 179
WLM setup
Java stored procedures 178
Java user-defined functions 178
WLM startup procedures
Java routines 178

X

XML
IBM Data Server Driver for JDBC and SQLJ 163
parameters
invoking routines from Java programs 96
XML data
Java applications 90
updating
tables in Java applications 91, 164
XML data retrieval
Java applications 93, 165
XML schemas
registering 99
removing 99
XMLCAST
SQLJ applications 167
xmlFormat property
binary XML format 98

Z

z/OS Application Connectivity to Db2 for z/OS
SMP/E jobs for loading 552
z/OS Application Connectivity to Db2 for z/OS feature
environment variables 553
z/OS Application Connectivity to z/OS
installing 551
z/OS UNIX System Services
accessing by Java routines 186

Product Number: 5650-DB2
5770-AF3

SC27-8846-02