

Security Server RACF Diagnosis Guide



Security Server RACF Diagnosis Guide

Note

Before using this information and the product it supports, be sure to read the general information under "Notices" on page 263.

Twelfth Edition, September 2008

This is a major revision of GA22-7689-10. This edition applies to Version 1 Release 10 of z/OS (5694-A01) and to all subsequent releases and modifications until otherwise indicated in new editions.

IBM welcomes your comments. A form for readers' comments may be provided at the back of this document, or you may address your comments to the following address:

International Business Machines Corporation MHVRCFS, Mail Station P181 2455 South Road Poughkeepsie, NY 12601-5400 United States of America

FAX (United States & Canada): 1+845+432-9405

FAX (Other Countries):

Your International Access Code +1+845+432-9405

IBMLink (United States customers only): IBMUSM10(MHVRCFS)

Internet e-mail: mhvrcfs@us.ibm.com

World Wide Web: http://www.ibm.com/systems/z/os/zos/webqs.html

If you would like a reply, be sure to include your name, address, telephone number, or FAX number.

Make sure to include the following in your comment or note:

- · Title and order number of this document
- · Page number or topic related to your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1994, 2008. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures	vi
Tables	ix
About this document	
Who should use this document	. x
How to use this document	. x
Where to find RACF information	χij
Where to find more information	χiν
IBM systems center publications	χiν
Other sources of information	X۷
To request copies of IBM publications	ΧV
Summary of changes	xvii
Chapter 1. Starting diagnosis	. 1
Planning for problem diagnosis	
Troubleshooting the problem	
Diagnosis hints	
Troubleshooting tables for problems in RACF	
Using the troubleshooting tables	
Troubleshooting tables	. 9
Performing a preliminary search for a matching problem	33
Introduction to searching for a matching problem	
Related information	
Steps for searching for a matching problem	
Examples of search arguments for RACF	
Chapter 2. Collecting and analyzing problem data	41
Collecting problem data	41
Obtaining a description of a RACF installation	41
Obtaining a system dump	41
Formatting a system dump	42
Obtaining RACF return codes and reason codes from a RACF macro	
invocation	42
Obtaining RACF return codes and reason codes from a RACF callable	
	43
Obtaining traces	43
Obtaining traces for program control and Program Access to Data Set	
(PADS) errors	
Obtaining traces on z/OS UNIX System Services	
Obtaining information about z/OS UNIX file and directory violations	
Obtaining trace records using the SET TRACE command	
Validating input	77
Identifying the caller of RACF	78
Checking the parameter list passed to RACF	79
Searching for a matching problem	80
Prerequisites	80
How to search for a matching problem	81
Application Identity Mapping Considerations	81
LOGREC data set entries for the alias index	
Recovering from errors with Application Identity Mapping	
Using SAF Trace to debug IBM HTTP server problems	

© Copyright IBM Corp. 1994, 2008

Before you begin													. 84 . 84 . 84
Chapter 3. Reporting RACF problems Prerequisites													. 99
How to report RACF problems to IBM .													
Chapter 4 Translachaeting value DAC	'E doto	boo	_										107
Chapter 4. Troubleshooting your RAC Format of the RACF database													
Header block (ICB)													
Templates													
Segment table block													
BAM blocks													
Index blocks													
Profiles													
Database Unload Utility for a RACF D													
Block Update command for a RACF of													
·		`			,								
Chapter 5. Error recovery for RACF R													139
Types of errors in an RRSF environmen													
Definition errors													
Environmental errors													
Program errors													141
Transmission and line errors													
Handshaking and state changes													
Connection states of RRSF nodes .													
Connection state changes after a suc													
Actions to recover from an RRSF failure													
RRSF ESTAE processing													
Failure of MVS System Service													
APPC errors													
Recording of errors											٠		148
Chapter 6. Diagnosis reference for RA	\CF												151
Parameter list descriptions			•		•	•	•	•	•	•		•	151
RACROUTE parameter list			•		•	•	•	•	•	•		•	152
· · · · · · · · · · · · · · · · · · ·					•	•	•	•	•	•	•	•	155
AUTH service parameter list						•	•	•	•	•	•	•	156
DEFINE service parameter list		•	•		•	•	•	•	•	•	•	•	160
DIRAUTH Service Parameter List .		•	•		•	•	•	•	•	•	•	•	166
EXTRACT service parameter list		•	•		•	•	•	•	•	•	•	•	167
FASTAUTH service parameter list .		•	•		•	•	•	•	•	•	•	•	169
LIST service parameter list			•		•	•	•	•	•	•	•	•	170
SIGNON service parameter list						•	•	•	•	•	•	•	171
STAT service parameter list						•	•	•	•	•	•	•	172
TOKENBLD service parameter list .								•					173
TOKENMAP/TOKENXTR service para												•	177
VERIFY/VERIFYX service parameter													178
ICHEINTY parameter list													182
Process flows for RACF				. '	•								185
Process flow for RACF commands .													185
Process flow for RACF directed comm													186

Process flow for RACF macros Process flow for RACF installation exits Process flow for RACF utilities. Process flow for RACF utilities. Process flow for the RACF Report Writer. Process flow for SMF Data Unload Utility (IRRADU00). Process flow for RACF Callable Services. Error recording for Callable Services. 193 Error recording for Callable Services. 194 Control Block overviews for RACF Callable Services. 194 Control Block overviews for RACF. 223 RCVT and SAF Router Vector Table. 223 ACEE and related Control Blocks. SVC dump title descriptions. 224 SVC failure (ICHRST00). 224 SVC failure (ICHRST00). 225 RACF initialization failure (ICHSEC02). 226 RACF COPY RACGLIST failure (IRRRLS12). 227 RACF CREATE RACGLIST failure (IRRRLS13). 228 RACF DELETE RACGLIST failure (IRRRLS14). 228 RACF data space recovery failure (IRRRLS15). 229
RACF subsystem failures (IRRSSC01, IRRSSS01, and IRRLOG00)
The DEBUG command
Appendix A. The Inventory Control Block (ICB)
Appendix B. The Security Product Trace Area (SAFT)
Appendix C. IPCS formatting for RACF control blocks257Using the VERBX RACFDATA command257Using the SUMMARY FORMAT command257Using the Control Block Formatters258
Appendix D. IBM Health Checker for z/OS
Appendix E. Accessibility261Using assistive technologies261Keyboard navigation of the user interface261z/OS information261
Notices

Policy for unsu	ppo	orte	ed l	nar	dw	are	.									265
Trademarks																265
Index																267

Figures

1.	Trace Output Showing a Problem in the Command Processor or RACF	
2.	Sample Proc 1: GTFRACF	. 53
3.	Sample Parmlib Member: GTFPRM#O	
4.	Information to Gather before Calling IBM with Abend Problems	
5.		
6.		
7.	·	
8.	and the second s	
	Information to Gather before Calling IBM with Message Problems	
	Information to Gather before Calling IBM with Performance Problems	
	Information to Gather before Calling IBM with Return Code Problems	
	Information to Gather before Calling IBM with Wait Problems	
	Format of the RACF Database	
	Template blocks	
	Block Masks of the RACF Database	
	Example of a RACF Index	
	Example Overview of a Level-1 Index Block	
	Example of an Index Block Header	
	Example Overview of an Alias Index Block	
	Example of Front-End Compression in an Index Block	
	Example of Index Entry for USR26 with a Base, TSO, and DFP Segment	
	Example of a Profile Displayed by BLKUPD	
	The Relationship between the BLKUPD Command and Its Levels of Subcommands	
24.	Flow of a Directed Command in an RRSF Environment	140
25.	RACROUTE Parameter List	153
26.	AUDIT Service Parameter List	155
27.	AUTH Service Parameter List	156
28.	DEFINE Service Parameter List	160
	DIRAUTH service parameter list	
	EXTRACT Service Parameter List	
	FASTAUTH Service Parameter List	
	LIST Service Parameter List	
	SIGNON Service Parameter List.	
	STAT Service Parameter List	
	TOKENBLD Service Parameter List	
	TOKENMAP/TOKENXTR Service Parameter List	
	VERIFY/VERIFYX Service Parameter List	
	ICHEINTY Parameter List	182
	Process Flow for RACF Commands	
	Process Flow for RACF Directed Commands	
41.		
42.		
43.		
44.	•	
45.		
46.	Process Flow for RACF Report Writer	
47.	•	
48.		193
49.	An Example of a Symptom Record when an SNAME is not found in the alias index entry but is	
	found in the mapping profile	196
50.	An Example of a Symptom Record when a UID is not found in the alias index entry but is found	
	in the mapping profile	198
51.	An Example of a Symptom Record when the Callable Service Cannot Communicate with RACF	220

vii

52.	An Example of a Symptom Record when a Command Fails
53.	Control Block Overview: RCVT and SAF Router Vector Table
54.	Control Block Overview: ACEE in a Single-User Address Space
55.	Control Block Overview: ACEE in a Multiple-User Address Space
56.	Control Block Overview: ACEEs When Third-Party AUTH Request Is Used
57.	Sample Symptoms for RACF (DAEDATA Output)
	Sample SDWA for RACF

Tables

Index to Troubleshooting Tables for RACF. Troubleshooting Table: Abends. Troubleshooting Table: Documentation. Troubleshooting Table: Incorrect Output Troubleshooting Table: Logon Problems. Troubleshooting Table: Loops. Troubleshooting Table: Messages. Troubleshooting Table: Performance Problems.	. 29
Troubleshooting Table: Documentation	. 19 . 20 . 28 . 29
Troubleshooting Table: Incorrect Output Troubleshooting Table: Logon Problems Troubleshooting Table: Loops Troubleshooting Table: Messages. Troubleshooting Table: Performance Problems	. 20 . 28 . 29
Troubleshooting Table: Logon Problems	. 28 . 29 . 29
Troubleshooting Table: Loops	. 29
Troubleshooting Table: Messages	. 29
Troubleshooting Table: Performance Problems	
	31
T 11 1 2 T11 D1 0 1	. 01
	. 32
Troubleshooting Table: Waits	. 33
Preliminary Search Symptoms for RACF	. 35
	. 37
RACF FMIDs	. 38
RMID Levels, yyy and zzzzz Values for Example 1	. 45
RMID Levels, yyy and zzzzz Values for Example 2	. 47
Callable services type numbers	. 55
RACROUTE CALL= service type number	. 56
Additional Search Symptoms for RACF	
Segment Identifiers	116
Table of New Connection States Based on a Successful TARGET Command	143
Contents of Primary Symptom String for a RACF Subsystem Address Space Error	149
Contents of Secondary Symptom String for a RACF Subsystem Address Space Error	150
Potential Contents of Variable Symptom String for a RACF Subsystem Address Space Error	150
Additional LOGREC Data for a RACF Subsystem Address Space Error	150
Cross-Reference for RACROUTE REQUEST=type, the Independent RACF System Macros, and	
Contents of Primary Symptom String for a Callable Service Error	194
Contents of Secondary Symptom String for a Callable Service Error	194
Additional LOGREC Data for a Callable Service Error	
Failing dataspace layer for an internal subroutine identifier	201
System service or internal check being performed	204
	Troubleshooting Table: Return Codes Troubleshooting Table: Waits Preliminary Search Symptoms for RACF Examples of Search Arguments for RACF RACF FMIDs RMID Levels, yyy and zzzzz Values for Example 1 RMID Levels, yyy and zzzzz Values for Example 2 Callable services type numbers RACROUTE CALL= service type number. Additional Search Symptoms for RACF Segment Identifiers Connection States between Nodes. Table of New Connection States Based on a Successful TARGET Command Contents of Primary Symptom String for a RACF Subsystem Address Space Error Contents of Secondary Symptom String for a RACF Subsystem Address Space Error Potential Contents of Variable Symptom String for a RACF Subsystem Address Space Error Cross-Reference for RACROUTE REQUEST=type, the Independent RACF System Macros, and the Parameter List Name Contents of Secondary Symptom String for a Callable Service Error Contents of Secondary Symptom String for a Callable Service Error Additional LOGREC Data for a Callable Service Error Contents of Secondary Symptom String for a Callable Service Error Additional LOGREC Data for a Callable Service Error Additional LOGREC Data for a Callable Service Error Failing dataspace layer for an internal subroutine identifier Failing system service for a failing system service identifier Indicator of R_cacheserv operation.

About this document

This document contains information about the Security Server for z/OS which consists of these components:

- Resource Access Control Facility (RACF)
- · DCE Security Server
- z/OS Firewall Technologies
- · Lightweight Directory Access Protocol (LDAP) Server
- · Open Cryptographic Services Facility
- · Security Server Network Authentication Service
- PKI Services

For information about the other components, see the documents related to those components.

This document provides information that is useful for diagnosing problems in RACF[®], such as:

- · Parameter list descriptions
- · Process flows
- · Control block overviews
- SVC dump title descriptions
- · A description of variable recording area (VRA) keys provided by RACF

The information included in this document should help you to:

- · Follow diagnostic procedures for each type of problem in RACF
- · Collect and analyze data needed to diagnose the problem
- Develop a search argument to be used for searching problem-reporting databases
- Gather the necessary problem data before reporting the problem to IBM[®]

In addition, this document describes how to use the BLKUPD command to correct problems in the RACF database.

Who should use this document

This document is for anyone who diagnoses problems that appear to be caused by RACF and for RACF system programmers who intend to use the BLKUPD command to correct problems in the RACF database.

This document assumes that you:

- · Understand basic system concepts and the use of system services
- · Code in assembler language and read assembler and linkage editor output
- Understand the commonly used diagnostic tasks and aids, such as message logs, system dumps, and the interactive problem control system (IPCS)
- · Understand the externals for RACF

How to use this document

Before using this document, collect this problem data:

- The problem type, such as an abend
- · An indication that the problem was caused by RACF

How to use this document


If you do not have this data, see the problem determination and diagnosis publications for your system and perform the recommended procedures.

Use this document to diagnose problems in RACF only. If the problem is not caused by RACF, return to your system diagnosis guide to identify the failing component or program.

Use this document to diagnose problems in RACF as follows:

- 1. Identify the problem type.
- 2. Collect problem data.
- 3. Analyze the problem data to develop symptoms.
- 4. Develop search arguments, search problem-reporting databases, and request the problem fix if the problem has been reported before. If not, continue diagnosis.
- 5. Collect additional problem data.
- 6. Analyze the problem data to isolate the problem.
- 7. Report the problem to IBM if assistance is needed or if the problem is new.

This flowchart illustrates the possible paths to be taken during problem analysis while using this document.



Where to find RACF information

For general RACF information, see the RACF web site at: http://www.ibm.com/servers/eserver/zseries/zos/racf/

For more detailed RACF information, see *z/OS Security Server RACF System Programmer's Guide*. For help in gathering information about your RACF installation, see your RACF security administrator and RACF auditor or see *z/OS Security Server RACF Security Administrator's Guide* and *z/OS Security Server RACF Auditor's Guide*.

For the syntax, return codes, and error reason codes for RACF macros, see *z/OS* Security Server RACF Macros and Interfaces except for the RACROUTE macro, which is described in *z/OS* Security Server RACROUTE Macro Reference.

For the mappings of RACF control blocks (such as the RCVT and the ACEE), see *z/OS Security Server RACF Data Areas*.

Where to find more information

Where necessary, this document references information in other documents. For complete titles and order numbers for all elements of z/OS®, see z/OS Information Roadmap.

Softcopy publications

The RACF library is available on the following CD-ROM, DVD, and online library collections. The collections include Softcopy Reader, which is a program that enables you to view the softcopy documents.

SK3T-4269 z/OS Version 1 Release 10 Collection

> This collection contains the set of unlicensed documents for the current release of z/OS in both BookManager® and Portable Document Format (PDF) files. You can view or print the PDF files with an Adobe Reader.

SK3T-4272 z/OS Security Server RACF Collection

> This softcopy collection kit contains the Security Server library for z/OS for multiple releases in both BookManager and Portable Document Format (PDF) formats. It also contains z/OS software product documents that contain substantial RACF information. This collection does not contain licensed publications.

SK3T-7876 IBM eServer zSeries Redbooks Collection

> This softcopy collection contains a set of documents called IBM Redbooks[™] that pertain to zSeries[®] subject areas ranging from e-business application development and enablement to hardware, networking, Linux®, solutions, security, Parallel Sysplex® and many others.

SK2T-2177 IBM Redbooks S/390 Collection

> This softcopy collection contains a set of documents called IBM Redbooks that pertain to S/390[®] subject areas ranging from application development and enablement to hardware, networking, security, Parallel Sysplex and many others.

RACF courses

The following RACF classroom courses are available in the United States:

H3917 Basics of z/OS RACF Administration

H3927 Effective RACF Administration

ES885 Exploiting the Advanced Features of RACF

ES840 Implementing RACF Security for CICS

IBM provides a variety of educational offerings for RACF. For more information about classroom courses and other offerings, do any of the following:

- · See your IBM representative
- Call 1-800-IBM-TEACh (1-800-426-8322)

IBM systems center publications

IBM systems centers produce documents known as IBM Redbooks® that can help you set up and use RACF. These documents have not been subjected to any formal review nor have they been checked for technical accuracy, but they represent current product understanding (at the time of their publication) and

Finding RACF information

provide valuable information on a wide range of RACF topics. They are not shipped with RACF; you must order them separately. A selected list of these documents follows. Other documents are available, but they are not included in this list, either because the information they present has been incorporated into IBM product manuals or because their technical content is outdated.

GG24-4282	Secured Single Signon in a Client/Server Environment
GG24-4453	Enhanced Auditing Using the RACF SMF Data Unload Utility
GG26-2005	RACF Support for Open Systems Technical Presentation Guide
SG24-4704	OS/390 Security Services and RACF-DCE Interoperation
SG24-4820	OS/390 Security Server Audit Tool and Report Application
SG24-5158	Ready for e-business: OS/390 Security Server Enhancements
SG24-6840	Communications Server for z/OS V1R2 TCP/IP Implementation Guide Volume 7: Security

Other sources of information

IBM provides customer-accessible discussion areas where RACF may be discussed by customer and IBM participants. Other information is also available through the Internet.

IBM discussion areas

IBM provides ibm.servers.mvs.racf newsgroup for discussion of RACF-related topics. You can find this newsgroup on news (NNTP) server news.software.ibm.com using your favorite news reader client.

Internet sources

The following resources are available through the Internet to provide additional information about the RACF library and other security-related topics:

Online library

To view and print online versions of the z/OS publications, use this address: http://www.ibm.com/systems/z/os/zos/bkserv/

Redbooks

The documents known as IBM Redbooks that are produced by the International Technical Support Organization (ITSO) are available at the following address: http://www.redbooks.ibm.com

Enterprise systems security

For more information about security on the S/390 platform, OS/390[®], and z/OS, including the elements that comprise the Security Server, use this address: http://www.ibm.com/systems/z/advantages/security/

RACF home page

You can visit the RACF home page on the World Wide Web using this address: http://www.ibm.com/servers/eserver/zseries/zos/racf/

· RACF-L discussion list

Customers and IBM participants may also discuss RACF on the RACF-L discussion list. RACF-L is not operated or sponsored by IBM; it is run by the University of Georgia.

To subscribe to the RACF-L discussion and receive postings, send a note to: listserv@listserv.uga.edu

Include the following line in the body of the note, substituting your first name and last name as indicated:

subscribe racf-1 first_name last_name

Finding RACF information

To post a question or response to RACF-L, send a note, including an appropriate Subject: line, to:

racf-1@listserv.uga.edu

· Sample code

You can get sample code, internally-developed tools, and exits to help you use RACF. This code works in our environment, at the time we make it available, but is not officially supported. Each tool or sample has a README file that describes the tool or sample and any restrictions on its use.

To access this code from a Web browser, go to the RACF home page and select the "Downloads" topic from the navigation bar, or go to www.ibm.com/servers/ eserver/zseries/zos/racf/goodies.html.

The code is also available from ftp.software.ibm.com through anonymous FTP. To get access:

- 1. Log in as user anonymous.
- 2. Change the directory, as follows, to find the subdirectories that contain the sample code or tool you want to download:

cd eserver/zseries/zos/racf/

An announcement will be posted on the RACF-L discussion list and on newsgroup ibm.servers.mvs.racf whenever something is added.

Note: Some Web browsers and some FTP clients (especially those using a graphical interface) might have problems using ftp.software.ibm.com because of inconsistencies in the way they implement the FTP protocols. If you have problems, you can try the following:

- Try to get access by using a Web browser and the links from the RACF home page.
- Use a different FTP client. If necessary, use a client that is based on command line interfaces instead of graphical interfaces.
- If your FTP client has configuration parameters for the type of remote system, configure it as UNIX[®] instead of MVS[™].

Restrictions

Because the sample code and tools are not officially supported,

- There are no guaranteed enhancements.
- No APARs can be accepted.

To request copies of IBM publications

Direct your request for copies of any IBM publication to your IBM representative or to the IBM branch office serving your locality.

There is also a toll-free customer support number (1-800-879-2755) available Monday through Friday from 8:30 a.m. through 5:00 p.m. Eastern Time. You can use this number to:

- · Order or inquire about IBM publications
- · Resolve any software manufacturing or delivery concerns
- Activate the program reorder form to provide faster and more convenient ordering of software updates

Summary of changes

Summary of changes for GA22-7689-11 z/OS Version 1 Release 10

The document contains information previously presented in *z/OS Security Server RACF Diagnosis Guide GA22-7689*, which supports z/OS Version 1 Release 9.

New information

- Chapter 4, "Troubleshooting your RACF database" has been updated to add CSDATA and CFDEF to the segment identifiers table.
- Appendix C, "IPCS formatting for RACF control blocks" has been added for IPCS formatting support for RACF control blocks.
- · ICHEINTY parameter list has been updated to add a new flag byte.

Changed information

- Appendix A, "The Inventory Control Block (ICB)" has been updated.
- See Using the BLKUPD command for updates on ALIAS index blocks.

Summary of changes for GA22-7689-10 z/OS Version 1 Release 9

The document contains information previously presented in z/OS Security Server RACF Diagnosis Guide GA22-7689, which supports z/OS Version 1 Release 8.

New information

- Chapter 6, "Diagnosis reference for RACF" has been updated to include new logrecs for R_Datalib.
- Chapter 6, "Diagnosis reference for RACF" has been updated to include a new tool to better analyze RACF dump information.

Changed information

• Appendix A, "The Inventory Control Block (ICB)" has been updated.

Summary of changes for GA22-7689-09 z/OS Version 1 Release 8

The document contains information previously presented in *z/OS Security Server RACF Diagnosis Guide GA22-7689*, which supports z/OS Version 1 Release 8.

New information

 FASTAUTH service parameter list has been updated to include a new CRITERIA parameter and AUTHCHKS=CRITONLY.

Summary of changes for GA22-7689-08 z/OS Version 1 Release 8

© Copyright IBM Corp. 1994, 2008

Summary of changes

The document contains information previously presented in *z/OS Security Server* RACF Diagnosis Guide GA22-7689, which supports z/OS Version 1 Release 7.

New information

- Appendix A, "The Inventory Control Block (ICB)" has been updated to include a new field, ICTMPXCT
- VERIFY/VERIFYX service parameter list has been updated to include new password phrase and SAF identity token fields.
- Templates has been updated to include a new template block structure.
- · Chapter 6, "Diagnosis reference for RACF" has been updated to include new logrecs for R_cacheserv and initACEE.

Changed information

Appendix A, "The Inventory Control Block (ICB)" has been updated.

You may notice changes in the style and structure of some content in this document—for example, headings that use uppercase for the first letter of initial words only, and procedures that have a different look and format. The changes are ongoing improvements to the consistency and retrievability of information in our documents.

This document contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

Chapter 1. Starting diagnosis

This information contains diagnostic procedures that you can perform with problem data that is quick and easy to obtain. It includes:

- · Planning for problem diagnosis
- · Troubleshooting the problem
- · Performing a preliminary search for a matching problem

Planning for problem diagnosis

Consider making these preparations for diagnosis before you use RACF:

- Install and operate RACF so that you get adequate problem data (such as messages and dumps) when problems occur.
- · Provide timely and complete backups of the RACF database.
- · Obtain access to a RACF user with the SPECIAL attribute.
- Reserve a RACF user ID with the SPECIAL attribute for use only after logon
 problems are resolved. For example, if all users logging on are, through an
 error, revoked when logging on, then even the system security administrator
 could be revoked when logging on. After the problem is corrected, the system
 security administrator could then log on with the user ID that is still active and
 activate the other user IDs.
- Obtain messages that have been sent to the system console or the security console.
- Prevent common problems by using RACF macros and utilities. See the recommendations in Utilities.
- Correct any problems that were caused while using RACF profiles and options.
 See z/OS Security Server RACF Security Administrator's Guide.

Troubleshooting the problem

This describes the RACF information you will need to trouble shoot your problem.

Diagnosis hints.

This information includes:

- How to make sure the problem is in RACF
- How to prevent some common programming errors in RACF macros and utilities
- Troubleshooting tables for problems in RACF.

These tables provide steps to follow in diagnosing each type of symptom, such as abend, message, or incorrect output.

Performing a preliminary search for a matching problem.

This information tells you how to search a database for a matching problem.

Note to the Reader

Chapter 4, "Troubleshooting your RACF database" describes how to use the BLKUPD command. The skills used in working with the BLKUPD command are different from the skills used in general troubleshooting for suspected RACF problems.

Diagnosis hints

This information provides advice on making sure that this is a problem with RACF and describes special types of problems that you might be able to fix without calling IBM.

If the recommendations that follow do not solve the problem, you need to follow the other diagnosis procedures described in the troubleshooting tables.

Making sure this is a RACF problem

Table 1 helps you make sure the problem is in RACF, rather than in either the caller of RACF or a system service used during processing of a RACF request.

For some problems, you might be able to do a quick check of the problem symptoms in the dump (if present), the job and system message log, SYS1.LOGREC, trace records, or other problem output.

Table 1. Determining Whether You Have a RACF Problem

Questions	Recommendations
Was there a valid request for a RACF function?	This could be that: • A RACF macro was invoked • A RACF utility was invoked • A RACF command was invoked • A user selected a RACF option on an ISPF panel The RACF request <i>must be valid</i> . A user request could invoke a routine that in turn invokes RACF. A RACF error message (like ICH408I, insufficient access authority) would then be issued not because of a RACF error or because of an error made by the original user, but because of the routine that invoked RACF. Note: If there is a system dump, you can check this in the trace records recorded in the dump. If there is no system dump, you may need to recreate the problem and request a system dump when the problem reoccurs.
Were error messages issued by system services that were used during RACF processing?	Check whether any error messages were issued for the user request, and make sure that message IDs are included with the messages. If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options specified: PROFILE WTPMSG MSGID.
Did RACF return control to the program that made the request?	For RACF macros and utilities: if there is a system dump, you can check this in the trace records recorded in the dump or (if an SVC was issued) in the RB chain in the system dump. If there is no system dump, you may need to recreate the problem and request a system dump when the problem reoccurs. For batch jobs, you can also check whether the job step for the program completed with a zero return code. (If an application program made the request, the TSO TEST command, a SLIP command issued by the system operator, or a WTO or PTRACE macro added to the program could be helpful in checking the execution steps within the program.)

Note: While diagnosing the problem, you need to continue to check whether something other than RACF might be the source of the problem. Possible candidates are:

- · Callers of RACF
- · System services used by RACF
- A hardware error
- A program that overlaid storage used by RACF, its caller, or a system service

A storage shortage can cause RACF commands to ABEND unpredictably

Common usage problems with RACF macros and utilities

This information provides advice for resolving problems that might result when using the RACF macros and utilities. The problems described here might appear at first to be errors in RACF.

Note: Advice for resolving coding problems is in *z/OS Security Server RACF System Programmer's Guide*.

Utilities

This information provides describes typical errors for RACF utilities and advice on action to take to resolve the problem.

IRRUT100 Utility

Error Assuming the utility is in a loop because it runs a long time. This

utility reads every profile in the RACF database and usually takes a

long time to run.

Action Run the utility when the system is not heavily used and allow it to

continue running until completion.

IRRUT200 Utility

Error

Assuming the RACF database contains no errors because the utility runs without error. The utility will not find all errors on a RACF database. Errors may exist within profiles and could result in message IRR407I.

RACE DATA SET SEQUENCE non denome SEADOU ON ont

RACF DATA SET SEQUENCE nnn, dsname SEARCH ON entry-name

where xxx is PRIMARY or BACKUP, nnn is the database sequence number, dsname is the data set name, and entry-name is the type of entry.

Action

If the utility does not find any errors, list the profiles involved using the appropriate RACF command. Look for error messages such as NO CONNECT ENTRY FOUND or incorrect data in fields such as OWNER.

Use the RACF commands to list and correct the profiles, if possible. If the commands fail, use BLKUPD to correct or delete the profiles.

RACF Sysplex Data Sharing

If RACF is enabled for sysplex communication and the system is operating in read-only mode, you cannot use BLKUPD to update the RACF database.

You can, however, run BLKUPD from another system (in the same data sharing group) that is not in read-only mode.

Error

Running the utility against an active output database. Even if there are no other users on the system, other system tasks and applications may be accessing the RACF database. If any changes are made to the database, the output of the utility will not be reliable.

Troubleshooting

Action Enter the RVARY INACTIVE or RVARY SWITCH command before

running the utility.

Error Assuming the run of the utility failed because a nonzero return code

was received.

Action The return code returned is the highest return code encountered

while processing the RACF database. A nonzero return code does not mean the utility failed. See *z/OS Security Server RACF*

Messages and Codes for details.

IRRUT400 Utility

Error Do not use this utility to merge RACF databases from separate

systems.

Action Use it only for merging back together a database from one system.

Error Ignoring return code 4 or return code 8 on IRRUT400 MERGE.

These return codes can indicate that duplicate profiles were found.

Ignoring them can result in profile conflicts.

Action Check the duplicate profiles on each of the input databases to

determine which ones are desired on the output database. Use the RACF commands to delete the unwanted ones and rerun the

IRRUT400 MERGE.

Error Running the utility against an active RACF database. Even if there

are no other users on the system, other system tasks and applications may be accessing the RACF database. If any changes

are made to the database, the output of the utility will not be

reliable.

Action Enter the RVARY INACTIVE or RVARY SWITCH command before

running the utility.

Error RACF manager return code X'50' (decimal 80) received while trying

to access the RACF database. This return code means that one of

these occurred:

 You attempted to update a RACF database that has had the utility run against it with the LOCKINPUT keyword specified.

RACF is enabled for sysplex communication and while running in

read-only mode, you tried to update the RACF database.

Action The LOCKINPUT keyword makes the input database unusable for system updates. It should be used with caution.

If your RACF database is locked, and you want to unlock it, use the

UNLOCKINPUT parameter of IRRUT400 or IRRDBU00.

Note: If this error occurs because your RACF sysplex data sharing system is in read-only mode, UNLOCKINPUT will not correct the problem. You cannot update the RACF database when

your system is operating in read-only mode.

IRRDBU00 Utility

Error RACF manager return code X'50' (decimal 80) received from

another task while trying to access the RACF database. This return

code means that one of these has occurred:

- A task attempted to update the RACF database while the IRRDBU00 utility was running against the database with the LOCKINPUT keyword specified.
- RACF is enabled for sysplex communication and was operating in read-only mode, when a task tried to update the RACF database.

Action

A task cannot update the database shared by a sysplex data sharing group when the system is operating in read-only mode. If, however, the utility is running with LOCKINPUT specified, do:

- · Wait until the utility is finished running.
- Run the utility at another time when updates are *not* needed.
- Run the utility against a copy of the RACF database—not against the active database.

Note: The LOCKINPUT keyword makes the input database for the utility temporarily unusable for system updates. It should be used with caution.

Error

I/O error while reading the database; your data set has slipped into secondary extents. These console messages appear:

13.31.20 JOB00019 *IRR401I 500 ABEND DURING RACF PROCESSING OF NEXT REQUEST FOR ENTRY MURPHYB
13.31.20 JOB00019 IRR401I 500 ABEND DURING RACF PROCESSING

These messages appear from SYSPRINT:

IRR67120I 500 abend during utility processing. Reason code 0000.
IRR67125I Utility ESTAE error routine will now attempt clean-up processing.

IRR67121I The module in control at time of abend was IRRDBU03.

Action

Reallocate the database that is causing the problem as a single extent. Recopy the data.

Error

Not all of your data is unloaded. Entire classes are missing.

Action

If you have imported a database from another system, you must use the class descriptor table from that system. IPL your system with the class descriptor table associated with the imported database.

Error

Fields are missing or field offsets are incorrect in the output database.

Action

Ensure that you have the current level of templates for the input database. Run IRRMIN00 with PARM=UPDATE and the current level of templates.

IRRRID00 Utility

Error

The RACF remove ID utility (IRRRID00) does not issue any user abends. If a user abend is received, it was issued by a called service such as DFSORT $^{\text{TM}}$.

Action

If you see a user abend, consult the documentation for the called service.

RACF Report Writer Utility (RACFRW)

Error The RACF report writer utility (RACFRW) does not issue any user

abends. If a user abend is received, it was issued by a called

service such as SORT.

Action If you see a user abend, consult the documentation for the called

service.

IRRIRA00

Error If the utility runs for a long period of time it is considered to be "in a

loop". When going from stage 0 to stage 1 (which can take a considerable amount of time), IRRIRA00 reads every mapping profile for the application identity mapping fields in the RACF database. It then reads the base profile named by the mapping profile to verify that the base profile-alias correlation is valid, and also to verify every user and group profile with an OMVS segment. For every valid correlation found, the alias index entry must be maintained. Additionally, when going from stage 2 to stage 3 (which can take a considerable amount of time), all application identity

mapping profiles in the RACF database are deleted.

Action Run the utility when the system is not being heavily used, and allow

it to continue running through completion.

RACF macros

This information provides describes typical errors for RACF macros and advice on action to take to resolve the problem.

General

Error

Unexpected return code or incorrect output when using the list and execute form of a macro. Results are not the same as for standard form.

Action

- 1. Check that the list form is in a CSECT, not a DSECT. If the list form is only in a DSECT, the parameter list will not be initialized.
- Check that the list form was copied over correctly into the GETMAIN work area.
- 3. Make sure the LIST and EXECUTE forms of the RACROUTE macro specify the same value for the RELEASE= parameter.

Error

Incorrect output from a macro with some keywords that were ignored.

Action

If the macro is continued on a second line, check that there is a continuation marked in column 72 and that the second line begins in column 16. If the macro is continued in column 17 or later, the assembler will ignore that line.

ICHEINTY Macro

Error

Incorrect output on an ICHEINTY macro when looking at discrete or generic profiles.

Action

Check the meaning of the GENERIC keyword. This keyword refers to the encoding of the resource name. It does not correspond to the type of profile returned. If the generic profile was retrieved, the high-order bit will be on at offset X'A' in the work area specified in the ICHEINTY macro. It will be off if a discrete profile was returned.

Error Difficulties while using the ICHEINTY macro.

Action Read the documentation of the macro very carefully. The ICHEINTY

macro and its related macros are quite complex. They bypass exits, naming conventions, authorization checking, and do little parameter validation. They are recommended only when there is no other way of accomplishing the desired task (no command or utility that will do the same thing). Note that in some cases, the RACXTRT macro

can be used instead of the ICHEINTY macro.

Error Message IRR401I reporting a DEQ abend (such as abend 730) or

abend 0C4 in IRRMRT00 on an ICHEINTY macro.

Action Check the specification of ENTRY or ENTRYX. This should point to

a 1-byte length followed by the ENTRY or ENTRYX NAME. If the length is zero, or if it points directly to the ENTRY or ENTRYX

name, an overlay occurs, resulting in the abend.

RACROUTE Macro

Error Abend 282-64 (decimal 100) on RACROUTE REQUEST=AUTH

macro with ACEE (accessor environment element) keyword, or abend 283-4C (decimal 76) on RACROUTE REQUEST=VERIFY

DELETE with ACEE keyword.

Action Check the specification of the ACEE keyword. On a

REQUEST=VERIFY, the ACEE keyword specifies a pointer to the address of the ACEE. On a REQUEST=AUTH, the ACEE keyword

specifies a pointer to the ACEE.

Error Return code 4, abend 282-20 (DECIMAL 32), or abend 0C4 during

parameter validation on RACROUTE REQUEST=AUTH macro.

Action Check the specification of the ENTITY keyword. If a variable name

is specified, it requires one set of parentheses. If a register is used,

it requires two sets of parentheses, as in ENTITY=((R4)).

Troubleshooting tables for problems in RACF

You need to be familiar with RACF's basic concepts and functions in order to use the troubleshooting tables. If you need more information, see page .

The troubleshooting tables that follow can help you:

- Select the type of problem that most closely matches your problem
- Follow procedures to diagnose each type of problem
- · Determine the symptoms to use to search for a matching problem
- Collect the information you need if you report the problem to IBM

Using the troubleshooting tables

Before you begin: You need to document the problem that you have and how it presents itself

Perform these steps to use the tables:

 First, determine which type of symptom best describes the problem that you are troubleshooting and locate that type in the first column, **Symptom Type**, in Table 2.

- 2. If you find a matching symptom type:
 - a. Go to the topic listed in the second column, **Refer To Topic...**, in Table 2. This is the appropriate troubleshooting table.
 - b. In the appropriate table, locate the specific RACF symptom for the problem (for example, Abends). In the second column, **Recommended Diagnostic Procedures**, in Table 3, follow the steps for diagnosing the problem.
- 3. If the problem has several symptoms, you should look up each symptom in the table. For example, some problems cause an abend and an I/O error message.

Table 2. Index to Troubleshooting Tables for RACF

Symptom Type	Refer To Topic
Abend	Abend troubleshooting table
Documentation error	Documentation troubleshooting table
Incorrect output	Incorrect output troubleshooting table
Logon problems	Logon problems troubleshooting table
Loop	Loops troubleshooting table
Messages	Messages troubleshooting table
Performance degradation	Performance problems troubleshooting table
Return code from RACF	RACF return codes troubleshooting table
Wait or hang	Waits troubleshooting table

If none of the symptoms in the list matches your problem, try these diagnostic procedures:

- 1. Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages.
 - If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID
- 2. If you find an error message that might relate to the problem, see Table 8.
- 3. If you don't have a system dump for the problem, and you want to request one, see Obtaining a system dump.
- 4. If you have a system dump for the problem, display or print the symptom record in the dump.
 - Use the IPCS VERBEXIT LOGDATA and VERBEXIT SYMPTOMS subcommands.

Note: SYMPTOMS has some prerequisite VERBEXITs, such as DAEDATA, which provide the abend and non-abend symptoms for the dump. You can also use the BLSCSCAN CLIST with IPCS to obtain the prerequisites. For details, see *z/OS MVS IPCS User's Guide*.

If the symptom record indicates an abend, loop, or wait, use the corresponding entry in the list of symptom types in Table 2.

If you have SYS1.LOGREC output for the problem, or a dump with LOGDATA output, check the LOGREC records related to the problem. If you have a software LOGREC record for an abend, use Table 3.

You know you are done when you have matched a system type with the type of problem you are having.

If you still don't have a symptom type,

- 1. Check the general problem analysis advice in *z/OS MVS Diagnosis: Reference*.
- 2. Read the information in Making sure this is a RACF problem.
- 3. If you need additional assistance, report the problem to IBM.

Troubleshooting tables

Abend troubleshooting table

Table 3 describes abends (abnormal end of task) related to RACF, including:

- RACF abends, which are abends that result from using RACF functions and that could occur under any operating system
- MVS abends, which are abends that MVS system services issue and that are unique to MVS

For RACF abends, the first digit indicates the type of problem, as shown in the table, and the second and third digits together indicate which SVC (supervisor call instruction) was associated with the abend. SVCs occur because a macro was invoked.

- SVC X'82' (in decimal, SVC 130) occurs because a RACHECK macro was invoked independently or by means of a RACROUTE REQUEST=AUTH.
- SVC X'83' (in decimal, SVC 131) occurs because a RACINIT macro was invoked independently or by means of a RACROUTE REQUEST=VERIFY.
- SVC X'84' (in decimal, SVC 132) occurs because a RACLIST macro was invoked independently or by means of a RACROUTE REQUEST=LIST.
- SVC X'85' (in decimal, SVC 133) occurs because a RACDEF macro was invoked independently or by means of a RACROUTE REQUEST=DEFINE.

Table 3. Troubleshooting Table: Abends

Symptom	Recommended Procedures for Abends							
Abends: X'0Cx'	Description: Program exception.							
	Action							
	1. Format the system dump.							
	2. In the PSW (program status word) in the dump, find the address of the failing instruction (the "next sequential instruction").							
	3. The address of the failing instruction should be an address that was available in the dump. Look in the dump for the eye-catcher prior to the failing instruction. (The hexadecimal values in the dump are usually interpreted along the right side of the dump. In a system dump that contains mostly unprintable characters, a readable name, such as the name of an object module, is easy to see.) The next eye-catcher prior to a failed instruction should include the name of the object module containing the failing instruction.							
	4. If the module name begins with ICH or IRR, RACF was executing when the abend occurred. Check these special cases first:							
	For 0C1 abends:							
	Use AMBLIST LISTLOAD to verify that the failing load module has been properly link-edited. Check the JCLIN as shipped with the RACF product. Pay particular attention to aliases and entry points. If IGC0013{ is the failing module, it might not have been properly link-edited.							
	Note: The last character in the load module name is X'C0'.							
	Determine whether the load module has been physically moved since it was link-edited. If the load module is in SYS1.LPALIB: a. Link-edit the load module again. b. Re-IPL with CLPA.							
	For 0C4 abends:							
	If the failing module is ICHCLD00, ICHDSM35, IRRRCK00, IRRRIN04, IRRRIN05, IRRRXT00, or IRRFLC00, it is likely that the module is trying to address a CSA or private profile that does not exist.							
	This can happen when a RACROUTE REQUEST=AUTH preprocessing exit passes a return code of 4 or 8 but does not build a CSA or private profile even though the CSA or private option was specified on the AUTH request.							
	To correct this error, correct the RACROUTE REQUEST=AUTH preprocessing exit so that it builds a CSA or private profile when requested on the AUTH request.							
	5. If these preliminary checks fail, check Identifying the caller of RACF to see if RACF is the probable cause of the problem or to determine who called the RACF module. Note: To check the parameters actually passed to RACF on a macro request, see Checking the parameter list passed to RACF.							
	6. If your investigation leads you to think that RACF was the cause of the problem, fill out the Information to Gather before Calling IBM with Abend Problems worksheet in Figure 4 and call the IBM support center.							

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends
Abends:	Description: RACF was unable to establish an ESTAE for the SVC (supervisor call instruction).
X'182' X'183'	Action
X'185'	1. See the message issued with the abend. This could be message IRR401I or ICH409I. Find the abend reason code, if any, in the text for the messages.
	2. See <i>z/OS Security Server RACF Messages and Codes</i> for information about the abend code and the accompanying message (if you haven't looked up the explanation already). In general, the information in <i>z/OS Security Server RACF Messages and Codes</i> should be sufficient to correct the problem.
	3. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, do the rest of the steps in this procedure.
	4. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this list.
	5. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.
	6. Format the system dump. See Formatting a system dump.
	7. You may want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.
	8. See Searching for a matching problem.
	9. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."
Abends: X'282'	Description: Parameter error on input to the SVC (supervisor call instruction). The reason codes associated with these abends indicate which parameter is bad in the parameter list. The bad parameter was probably set by the caller of RACF.
X'283'	Action
X'285'	See the message issued with the abend. This could be message IRR401I or ICH409I. Find the abend reason code, if any, in the text for the messages.
	2. If you haven't looked up the explanations already, see <i>z/OS Security Server RACF Messages and Codes</i> for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the reason code associated with the abend. In general, the information in <i>z/OS Security Server RACF Messages and Codes</i> should be sufficient to correct the problem.
	3. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, follow the rest of the steps in this procedure.
	4. Check whether any other error messages were issued with the abend messages. These messages might indicate the context in which the abend occurred. In particular, messages preceding the abend message might indicate conditions that caused the abend. Note: If message IDs were not included with the messages and you can re-create the error, do:
	 If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified.
	 If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends
Abends: X'282'	5. Find the name of the calling module. This is the module that issued the RACF request (such as a RACF macro, command, or utility). The conditions set up by this module might have caused the abend.
X'283'	See Identifying the caller of RACF.
X'285' (continued)	6. Find the owner of the module: an IBM product, a non-IBM product, or a user at your installation.
	If the module name begins with ICH or IRR, it is a RACF module. Continue with this procedure.
	If the module name begins with the letters A through I, S, or X (but not ICH or IRR), it is probably part of an IBM product, but it is not RACF. See the diagnosis or logic document for the program of which the module is a part. To determine the name of the component that owns the module, use the component summary in <i>z/OS MVS Diagnosis: Reference</i> .
	7. See Performing a preliminary search for a matching problem.
	If you find a matching problem, apply the appropriate PTFs (program temporary fixes).
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the steps in the rest of this procedure. Please be sure to fill out a blank copy of the worksheet shown in Figure 4.
	8. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. You may want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.
	9. See Searching for a matching problem.
	10. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."
Abends:	Description: A user exit associated with an SVC (supervisor call instruction) passed an non-valid return code.
X'382'	Action
X'383' X'385'	See the message issued with the abend. This could be message IRR401I or ICH409I.
X 303	If you haven't looked up the explanations already, see <i>z/OS Security Server RACF</i>
	Messages and Codes for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the explanation of the abend code. In general, the information in z/OS Security Server RACF Messages and Codes should be sufficient to correct the problem.
	3. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, do the rest of the steps in this procedure.
	4. Check whether any other error messages were issued with the abend messages. These messages might indicate the context in which the abend occurred. In particular, messages preceding the abend message might indicate conditions that caused the abend. Note: If message IDs were not included with the messages and you can re-create the error, do:
	 If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified.
	If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends
Abends: X'382'	5. Find the name of the calling module. This is the module that issued the RACF request (such as a RACF macro, command, or utility). The conditions set up by this module might have caused the abend.
X'383'	See Identifying the caller of RACF.
X'385' (continued)	Find the owner of the module: an IBM product, a non-IBM product, or a user at your installation.
	If the module name begins with ICH or IRR, it is a RACF module. Continue with this procedure.
	If the module name begins with the letters A through I, S, or X (but not ICH or IRR), it is probably part of an IBM product, but it is not RACF. See the diagnosis or logic document for the program of which the module is a part. To determine the name of the component that owns the module, use the component summary in <i>z/OS MVS Diagnosis: Reference</i> .
	7. See Performing a preliminary search for a matching problem.
	If you find a matching problem, apply the appropriate PTFs (program temporary fixes).
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this procedure. Please be sure to fill out a blank copy of the worksheet shown in Figure 4.
	8. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.
	Format the system dump. See Formatting a system dump.
	10. You might want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.
	11. See Searching for a matching problem.
	12. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."
Abends: X'3C7'	Description: RACF storage manager error during processing of a non-SVC, SRB mode, get space and free space request.
	Action
	1. See the message issued with the abend. This could be message ICH409I. Find the abend reason code, if any, in the text for the message.
	2. If you haven't looked up the explanations already, see z/OS Security Server RACF Messages and Codes for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the reason code associated with the abend. In general, the information in z/OS Security Server RACF Messages and Codes should be sufficient to correct the problem.
	3. See Chapter 3, "Reporting RACF problems to IBM."

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends
Abends: X'400'	Description: This abend is issued by IOS (I/O supervisor) when the RACF database goes into multiple extents. (The RACF database must be allocated in a single contiguous extent.)
	Action
	To correct this problem, reallocate the RACF database with enough space to fit in a single extent and re-IPL the system.
	2. If this step does not solve the problem, do the rest of the steps in this procedure.
	3. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this list.
	4. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.
	5. Format the system dump. See Formatting a system dump.
	6. You might want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.
	7. See Searching for a matching problem.
	8. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."
Abends:	Description: RACF manager error during SVC (supervisor call instruction) processing.
X'482'	Action
X'483' X'485'	 See the message issued with the abend. This could be message IRR401I or ICH409I. Find the abend reason code, if any, in the text for the messages.
	See message IRR413I, which occurs with RACF manager abends. Find the RACF manager request ID in the message.
	3. See z/OS Security Server RACF Messages and Codes for information about the abend code and the accompanying message (if you haven't looked up the explanation already). In general, the information in z/OS Security Server RACF Messages and Codes should be sufficient to correct the problem.
	4. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, do the rest of the steps in this procedure.
	5. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this list.
	6. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.
	7. Format the system dump. See Formatting a system dump.
	8. You might want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.
	9. See Searching for a matching problem.
	10. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends
Abends: X'4C6'	Description: A service call to a RACF module used for z/OS UNIX services did not complete. The specific error is indicated by the abend reason code.
	Action
	1. See the message issued with the abend. This could be message ICH409I. Find the abend reason code , if any, in the text for the message .
	2. If you haven't looked up the explanations already, see <i>z/OS Security Server RACF Messages and Codes</i> for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the reason code associated with the abend. In general, the information in <i>z/OS Security Server RACF Messages and Codes</i> should be sufficient to correct the problem.
	3. See Chapter 3, "Reporting RACF problems to IBM."
Abends: X'4C7'	Description: RACF storage manager error during processing of a non-SVC, task mode, get space and free space request.
	Action
	1. See the message issued with the abend. This could be message ICH409I. Find the abend reason code, if any, in the text for the message.
	2. If you haven't looked up the explanations already, see z/OS Security Server RACF Messages and Codes for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the reason code associated with the abend. In general, the information in z/OS Security Server RACF Messages and Codes should be sufficient to correct the problem.
	3. See Chapter 3, "Reporting RACF problems to IBM."
Abends:	Description: Error during SVC (supervisor call instruction) processing. The specific error is indicated by the abend reason code.
X'582'	Action
X'585'	 See message IRR401I or ICH409I, which occur with RACF abends. Find the abend reason code, if any, in the message text. If the abend reason code is zero, no ACEE (accessor environment element) could be found. Note: This is normal if a job started or a user logged on while RACF was inactive but has since been reactivated.
	2. If the abend reason code is not zero, do the rest of the steps in this procedure.
	3. If you haven't looked up the explanations already, see <i>z/OS Security Server RACF Messages and Codes</i> for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the reason code associated with the abend. In general, the information in <i>z/OS Security Server RACF Messages and Codes</i> should be sufficient to correct the problem.
	4. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, do the rest of the steps in this procedure.
	5. Check whether any other error messages were issued with the abend messages. These messages might indicate the context in which the abend occurred. In particular, messages preceding the abend message might indicate conditions that caused the abend. Note: If message IDs were not included with the messages and you can re-create the error, do:
	 If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified.
	 If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends
Abends: X'582' X'585' (continued)	6. Find the name of the calling module. This is the module that issued the RACF request (such as a RACF macro, command, or utility). The conditions set up by this module migh have caused the abend.
	See Identifying the caller of RACF.
	7. Find the owner of the module: an IBM product, a non-IBM product, or a user at your installation.
	If the module name begins with ICH or IRR, it is a RACF module. Continue with this procedure.
	If the module name begins with the letters A through I, S, or X (but not ICH or IRR), it is probably part of an IBM product, but it is not RACF. See the diagnosis or logic document for the program of which the module is a part. To determine the name of the component that owns the module. use the component summary in <i>z/OS MVS Diagnosis: Reference</i> .
	8. See Performing a preliminary search for a matching problem.
	If you find a matching problem, apply the appropriate PTFs (program temporary fixes).
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this procedure. Please be sure to fill out a blank copy of the worksheet shown in Figure 4.
	9. If the abend did not generate a system dump, and the problem is reproducible, obtain a
	system dump. See Obtaining a system dump.
	10. Format the system dump. See Formatting a system dump.
	11. You might want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.
	12. See Searching for a matching problem.
	13. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."
Abends: X'683'	Description: Insufficient authority to issue the SVC (supervisor call) instruction. The issuer of the SVC must be APF-authorized (authorized program facility). These abends can occur if a RACF command is not in the TSO command table.
X'684'	Action
X'685'	 See the message issued with the abend. This could be message IRR401I or ICH409I. Find the abend reason code, if any, in the text for the messages.
	2. If you haven't looked up the explanations already, see <i>z/OS Security Server RACF Messages and Codes</i> for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the reason code associated with the abend. In general, the information in <i>z/OS Security Server RACF Messages and Codes</i> should be sufficient to correct the problem.
	3. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, do the rest of the steps in this procedure.
	4. Check whether any other error messages were issued with the abend messages. These messages might indicate the context in which the abend occurred. In particular, messages preceding the abend message might indicate conditions that caused the abend. Note: If message IDs were not included with the messages and you can re-create the error, do:
	• If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified.
	If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	5. Find the name of the calling module. This is the module that issued the RACF request (such as a RACF macro, command, or utility). The conditions set up by this module might
	have caused the abend.

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends	
Abends:	Find the owner of the module: an IBM product, a non-IBM product, or a user at your installation.	
X'683' X'684'	If the module name begins with ICH or IRR, it is a RACF module. Continue with this procedure.	
X'685' (continued)	If the module name begins with the letters A through I, S, or X (but not ICH or IRR), it is probably part of an IBM product, but it is not RACF. See the diagnosis or logic document for the program of which the module is a part. To determine the name of the component that owns the module, use the component summary in <i>z/OS MVS Diagnosis: Reference</i> .	
	7. See Performing a preliminary search for a matching problem.	
	If you find a matching problem, apply the appropriate PTFs (program temporary fixes).	
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this procedure. Please be sure to fill out a blank copy of the worksheet shown in Figure 4.	
	8. If the SVC (supervisor call instruction) was issued because a user issued a RACF command, check to be sure the RACF command is in the list of APF-authorized (authorized program facility) commands or in the ISPF command tables.	
	9. See Performing a preliminary search for a matching problem.	
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this list.	
	10. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.	
	11. Format the system dump. See Formatting a system dump.	
	12. You might want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.	
	13. See Searching for a matching problem.	
	14. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."	
Abends: X'9C7'	Description: RACF token error during RACROUTE functions.	
	Action	
	 See the message issued with the abend. Find the abend reason code, if any, in the text for the messages. 	
	2. See <i>z/OS Security Server RACF Messages and Codes</i> for information about the abend code and the accompanying message (if you haven't looked up the explanation already). In general, the information in <i>z/OS Security Server RACF Messages and Codes</i> should be sufficient to correct the problem.	
	3. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, do the rest of the steps in this procedure.	
	4. See Performing a preliminary search for a matching problem.	
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this list.	
	5. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.	
	6. Format the system dump. See Formatting a system dump.	
	7. You might want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.	
	8. See Searching for a matching problem.	
	9. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."	

Abends

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends	
Abends: X'AC5'	Description: Internal RACF problem.	
	Action	
	1. See Performing a preliminary search for a matching problem.	
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this list.	
	2. Format the system dump. See Formatting a system dump.	
	3. See Searching for a matching problem.	
	4. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."	
Abends:	Description: RACF storage manager error during SVC processing.	
X'D82'	Action	
X'D83'	1. See the message issued with the abend. This could be message IRR401I or ICH409I.	
X'D84'	Find the abend reason code, if any, in the text for the messages.	
X'D85'	2. If you haven't looked up the explanations already, see <i>z/OS Security Server RACF Messages and Codes</i> for the explanations of the message and the abend code. (Abend codes are also called "completion codes.") Pay particular attention to the reason code associated with the abend. In general, the information in <i>z/OS Security Server RACF Messages and Codes</i> should be sufficient to correct the problem.	
	3. If the information in <i>z/OS Security Server RACF Messages and Codes</i> is not sufficient to correct the problem, do the rest of the steps in this procedure.	
	4. Check whether any other error messages were issued with the abend messages. These messages might indicate the context in which the abend occurred. In particular, messages preceding the abend message might indicate conditions that caused the abend. Note: If message IDs were not included with the messages and you can re-create the error, do:	
	 If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. 	
	 If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID. 	
	5. Find the name of the calling module. This is the module that issued the RACF request (such as a RACF macro, command, or utility). The conditions set up by this module might have caused the abend.	
	See Identifying the caller of RACF.	

Table 3. Troubleshooting Table: Abends (continued)

Symptom	Recommended Procedures for Abends	
Abends:	Find the owner of the module: an IBM product, a non-IBM product, or a user at your installation.	
X'D82' X'D83' X'D84'	If the module name begins with ICH or IRR, it is a RACF module. Continue with this procedure.	
X D84 X'D85' (continued)	If the module name begins with the letters A through I, S, or X (but not ICH or IRR), it is probably part of an IBM product, but it is not RACF. See the diagnosis or logic document for the program of which the module is a part. To determine the name of the component that owns the module, use the component summary in z/OS MVS Diagnosis: Reference.	
	7. See Performing a preliminary search for a matching problem.	
	If you find a matching problem, apply the appropriate PTFs (program temporary fixes).	
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the steps in the rest of this procedure. Please be sure to fill out a blank copy of the worksheet shown in Figure 4.	
	8. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.	
	9. Format the system dump. See Formatting a system dump.	
	10. You may want to re-create the problem you are investigating (or set up the conditions to allow the problem to reoccur) after setting the trap to obtain the dump.	
	11. See Searching for a matching problem.	
	12. If you still do not find a matching problem, see Chapter 3, "Reporting RACF problems to IBM."	
Abends:	Description: RACF is not installed.	
X'E82' X'E83' X'E84' X'E85'	Action Make sure RACF is properly installed.	

Documentation troubleshooting table

Table 4. Troubleshooting Table: Documentation

Symptom	Recommended Procedures for Documentation
Error in a publication that	Action
documents RACF	 If you have a problem with RACF documentation, consider using the Readers' Comment form at the back of that document to report the documentation error. You have your choice of mailing in a hardcopy comment sheet (the "Readers' Comments" form) or sending us the comment by FAX or electronic mail (see the "Communicating Your Comments to IBM" page in the back). Report the problem to the IBM support center for these situations: The correction to the documentation is needed to prevent a severe problem. You are not sure if the error is in the documentation or the product. The error is in an online panel.
	2. If you plan to report the problem to the IBM support center, see:
	a. Performing a preliminary search for a matching problem
	b. Searching for a matching problem
	c. Chapter 3, "Reporting RACF problems to IBM"

Incorrect output troubleshooting table

This topic describes incorrect output from RACF. Generally, incorrect output can be missing records, duplicate records, incorrect values, format errors, or meaningless data.

Incorrect output could also be the improper issuing of an error message, an abend code, a return code from a macro, or a wait-state code. For example, an abend could be issued when no abend is needed, or a message that should be issued is not issued. Another example is message text that includes incorrect information.

Table 5. Troubleshooting Table: Incorrect Output

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: Improper	Action
access to a protected resource with no message issued	Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages.
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	2. Check the global access checking table for an entry describing the resource. This step does not apply for z/OS or OS/390 z/OS UNIX System Services .
	3. Check for an installation exit for RACROUTE REQUEST=AUTH. This step does not apply for z/OS or OS/390 z/OS UNIX System Services .
	4. Check the kind of RACROUTE request that was made. Compare it with the level of protection of the resource. (Use LISTDSD or RLIST command for the resource; use LISTUSER command for the user.) This step does not apply for z/OS or OS/390 z/OS UNIX System Services.
	5. If the cause of the problem is not apparent, attempt to duplicate the problem with another user doing the same kind of request. Try another user with similar attributes and group associations. If the problem can be duplicated, then determine which user attributes or group associations cause the problem. This can help you define the problem. If the problem cannot be duplicated with other users, try to duplicate the problem with other resources protected like the original.
	6. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.
	7. Get a printed or online copy of the incorrect output. You need it to analyze the problem or report the problem to IBM.
	8. See Searching for a matching problem.
	9. See Chapter 3, "Reporting RACF problems to IBM."

Table 5. Troubleshooting Table: Incorrect Output (continued)

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: Messages	Action
	Make sure you have all the error messages that were issued for the user request, and make sure that message IDs are included with the messages.
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	 Decide which of these types of messages applies: a. Macro error messages (MNOTEs) b. System error messages issued by RACF (messages with prefixes of CST, HCP, ICH, IRR, and RPI)
	3. Decide what the nature of the message error is.
	 a. Was the message valid but unexpected? See Messages troubleshooting table.
	b. Was the message itself incorrect; for example, did it contain incorrect or unreadable data, or was an error message issued for a non-error situation?
	 If you had incorrect output from a RACF macro, see Utilities for a list of common application programming errors for RACF; the results of some of these errors could appear to be incorrect output from RACF.
	5. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM using the procedures in the remainder of this list.
	6. Get a printed or online copy of the incorrect output. You need it to analyze the problem or report the problem to IBM.
	 For macro error messages (MNOTEs): Get a copy of the assembler listing that contained the macro error message.
	b. For system error messages issued by RACF: Get a copy of the part of the job log or system log that contained the message. (The IBM support center might also need to check messages that preceded the error message in the log.)
	7. See Searching for a matching problem.
	8. See Chapter 3, "Reporting RACF problems to IBM."

Incorrect output

Table 5. Troubleshooting Table: Incorrect Output (continued)

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: Incorrect	Action
abends	Check whether any error messages were issued in response to the user request and make sure that message IDs are included with the messages.
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	2. Decide what the nature of the abend error is.
	a. Was the abend valid but unexpected? Go to Abend troubleshooting table.
	 b. Was the abend not documented? Go to Documentation troubleshooting table.
	c. Was the abend itself incorrect? For example, was the abend issued for a non-error situation?
	d. If you had incorrect output from a RACF macro, see Utilities for a list of common application programming errors for RACF; the results of some of these errors could appear to be incorrect output from RACF.
	3. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.
	4. Get a printed or online copy of the incorrect output. You need it to analyze the problem or report the problem to IBM.
	To Get the Dump Output and Analysis Results:
	Use the procedures described: a. Obtaining a system dump, if you need to request a dump b. Formatting a system dump c. Validating input.
	5. See Searching for a matching problem.
	6. See Chapter 3, "Reporting RACF problems to IBM."

Table 5. Troubleshooting Table: Incorrect Output (continued)

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: Improperly	Action
formatted output from RACF LIST commands (LISTDSD, LISTGRP, LISTUSER, RLIST,	 Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages.
and RACLINK LIST)	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	2. Decide what caused the incorrect output:
	 The data read by the command (the RACF database). If this is the case, see the table entry for the RACF database.
	 RACF's processing of the command request
	3. If the database should have been updated by a command that was issued on another system in the RACF remote sharing facility (RRSF) network, check the status of the connection with a TARGET LIST on this system and the originating system. Also, check the RRSFDATA profiles on the originating system.
	4. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.
	5. Get a printed or online copy of the incorrect output. You need it to analyze the problem or report the problem to IBM.
	You can capture the output by executing the command in a batch job, or under the session manager, or in a CLIST in which you trap the output from the command.
	6. See Searching for a matching problem.
	7. See Chapter 3, "Reporting RACF problems to IBM."
Incorrect output: Improperly	Action
formatted reports (from DSMON or RACF report writer)	 Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages.
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	2. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.
	Get a printed or online copy of the improperly formatted report. You need it to analyze the problem or report the problem to IBM.
	4. Check whether the problem is caused by RACF in generating the report or by bad data used as input to the report:
	As a check on the RACF report writer, you can print (or display) the SMF (system management facility) records using the access method services PRINT command with DUMP specified.
	As a check on DSMON, use the RACF LIST commands to check the profiles that seem to be reported incorrectly by DSMON.
	5. See Searching for a matching problem.
	6. See Chapter 3, "Reporting RACF problems to IBM."

Incorrect output

Table 5. Troubleshooting Table: Incorrect Output (continued)

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: SMF records	Action
(types 80, 81, or 83)	 Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages.
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	If the RACF SMF data unload utility leads you to suspect that the SMF (system management facilities) records are not valid, check to make sure that the SMF records are at fault, not the utility.
	3. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.
	4. Get a printed or online copy of the incorrect output. You need it to analyze the problem or report the problem to IBM.
	For SMF records (type 80 or 81):
	 Use the RACF SMF data unload utility to list the contents of the RACF SMF records. See z/OS Security Server RACF Auditor's Guide for more information.
	 As a check on the RACF SMF data unload utility, you can print (or display) the record using the access method services PRINT command with HEX specified.
	See Searching for a matching problem.
	See Chapter 3, "Reporting RACF problems to IBM."

Table 5. Troubleshooting Table: Incorrect Output (continued)

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: The RACF database (this includes profiles, index blocks, and inventory	Action
	Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages.
control block)	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	2. These RACF functions affect the RACF database:
	 RACF commands that add, alter, or delete profiles (such as ADDUSER, ALTUSER, DELUSER, RDEFINE, RALTER, and RDELETE)
	BLKUPD command
	RVARY and SETROPTS commands
	IRRUT400 utility
	 RACF macros: RACDEF, RACINIT, ICHEINTY, ICHETEST, ICHEACTN, and RACXTRT (with ENCRYPT or TYPE=REPLACE specified)
	3. If the database should have been updated by a command that was issued on another system in the RACF remote sharing facility (RRSF) network, check the status of the connection with a TARGET LIST on this system and the originating system. Also, check the RRSFDATA profiles on the originating system.
	4. If you had incorrect output from a RACF macro, see Utilities for a list of common application programming errors for RACF; the results of some of these errors could appear to be incorrect output from RACF.
	5. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.
	6. Get a printed or online copy of the incorrect output. You need it to analyze the problem or report the problem to IBM. Run the IRRUT200 utility and the BLKUPD command to get a description of the RACF database. See <i>z/OS Security Server RACF System Programmer's Guide</i> for a description of how to use IRRUT200, and Block Update command for a RACF database (BLKUPD) for a description of how to use BLKUPD.
	7. See Searching for a matching problem.
	8. See Chapter 3, "Reporting RACF problems to IBM."

Incorrect output

Table 5. Troubleshooting Table: Incorrect Output (continued)

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: RACF	Action
subsystem	 Check for any messages that might have been issued by the RACF subsystem.
	2. Refer to z/OS Security Server RACF Messages and Codes.
	3. If the RVARY command, along with other commands, is not working, then the subsystem is also not working correctly.
	Check to see if the subsystem initialized correctly; if it did not, check for an install problem and get a system console log (SYSLOG).
	5. If a <i>userid</i> .RRSFLIST data set is missing output, or contains incorrect output:
	 Issue the SET LIST command and verify that:
	 Automatic direction or password synchronization is active for the type of request for which output is missing.
	 The OUTPUT keyword specifies the user ID that should be receiving the missing output.
	 The correct level of output is specified (ALWAYS, WARN, or FAIL).
	 Check the RRSFDATA profiles and access lists and make sure that the requests are really being directed.
	 Check the TSO PREFIX specification for the user ID that is missing the output. If it is set to something other than the user ID, the RRSFLIST data set might have a different name than you expect.
	 Issue the TARGET LIST command on both nodes involved, and make sure that they are both operative-active, and that requests are not queued in one of the INMSG or OUTMSG data sets.
	 Check whether anyone stopped the RACF subsystem address space, or used the TARGET command to purge an INMSG or OUTMSG file while a request was active. These actions can cause requests and output to be lost.
	 Check for TSO TRANSMIT messages to the user ID that is missing the output. If there was an error processing the RRSFLIST data set a message should have been sent. Check the console log too.
	 Make sure the RRSFLIST data set is allocated with the proper DCB parameters and is not full. If in doubt, you can delete or rename it and let RACF create another one.
	6. If an abend occurred, get a copy of the system dump that was taken.
	7. If the abend did not generate a system dump, and the problem is reproducible, obtain a system dump. See Obtaining a system dump.
	8. Format the system dump. See Formatting a system dump.

Table 5. Troubleshooting Table: Incorrect Output (continued)

Symptom	Recommended Procedures for Incorrect Output
Incorrect output: Return or	Action
reason code from a RACF macro or utility	Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages.
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.
	2. Decide if the return or reason code is:
	Incorrect
	Undocumented. See Documentation troubleshooting table.
	3. See Utilities for a list of common application programming errors for RACF; the results of some of these errors could appear to be incorrect output from RACF.
	4. See Performing a preliminary search for a matching problem.
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.
	5. Get a printed or online copy of the incorrect output. You need it to analyze the problem or report the problem to IBM.
	Note: If the macro return code or reason code was incorrect, request a system dump from a RACF macro request that produced the incorrect output when RACF returns control.
	To Get the Dump Output and Analysis Results:
	Use the procedures described in these areas: a. Obtaining a system dump, if you need to request a dump b. Formatting a system dump c. Validating input.
	6. See Searching for a matching problem.
	7. See Chapter 3, "Reporting RACF problems to IBM."

Logon problems troubleshooting table

Table 6. Troubleshooting Table: Logon Problems

Symptom	Recommended Procedures for Logon Problems		
Users cannot log on	Action		
	 Check whether any error messages were issued for the user request and make sure that message IDs are included with the messages. If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID. 		
	2. If only one or a few users cannot log on, check that they are using the current password. If no users can log on, do the rest of this procedure.		
	3. There might be a password synchronization problem, which you should be able to recognize because the user's old password is either accepted as correct or as expired. Enter a RACLINK LIST command on each system to check the user's user ID association if that's what is being used to synchronize passwords.		
	4. If the database should have been updated by a command that was issued on another system in the RACF remote sharing facility (RRSF) network, check the status of the connection with a TARGET LIST on this system and the originating system. Also, check the RRSFDATA profiles on the originating system.		
	5. Check the system date in effect for the current system IPL. If the wrong date is in effect, users who cannot log on might have the REVOKE attribute in their user profiles. See z/OS Security Server RACF Security Administrator's Guide for more information on the REVOKE attribute.		
	6. If you are sharing your database with other systems, make sure that all systems sharing the database are using the same password authentication algorithm, and that there has not been a period of time when the systems were using different algorithms.		
	The default password authentication algorithm for the RACF component of the SecureWay® Security Server is the Data Encryption Standard (DES) algorithm. The default password authentication algorithm for RACF on MVS beginning with RACF 2.1 is the (DES) algorithm, but for releases previous to RACF 2.1 the default is the masking algorithm. Make sure that you have taken the correct steps to activate the algorithm that you intend to use on each system sharing the database. See <i>z/OS Security Server RACF System Programmer's Guide</i> for more information.		
Users cannot log on (continued)	 7. If you are using a PassTicket, make sure: The PTKTDATA class has been activated and a class profile exists. You do not try to use the same PassTicket more than once. The GMT clock on the evaluating computer is within the valid time range. 		
	For more information, see <i>z/OS Security Server RACF Security Administrator's Guide</i> .		
	8. See Performing a preliminary search for a matching problem.		
	If you do not find a matching problem, you need to collect problem information to report to IBM, using the procedures in the remainder of this list.		
	Get a printed or online copy of the SMF records related to the logon problem.You need it to analyze the problem or report the problem to IBM.		
	10. See Searching for a matching problem.		
	11. See Chapter 3, "Reporting RACF problems to IBM."		

Loops troubleshooting table

Table 7. Troubleshooting Table: Loops

Symptom	Recommended Procedures for Loops		
Any loop during	Action		
RACF processing	1. Check whether any error messages were issued for the user request that had the loop and make sure that message IDs are included with the messages. If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.		
	2. Check whether the prefix of one of the modules involved in the loop is ICH or IRR. Note: The instructions involved in the loop are generally pointed to by the PSW that was active when the system dump was generated. Most modules owned by IBM have an identifier with the module name at either the beginning or end of the object code for the module. See the MVS diagnosis publications if you need further details of general loop analysis techniques.		
	3. If the prefix is ICH or IRR, the problem might be caused by RACF, and you should use these diagnostic procedures:		
	a. Check that the problem was not due to repeated requests for RACF services. Repeated requests might be caused by a loop of logic in the application program issuing the request. If the loop was in a program making repeated requests, report the problem to the owner of the program. If the loop was within RACF, use the diagnostic procedures in the remainder of this list.		
	b. See Performing a preliminary search for a matching problem.		
	c. If you do not find a matching problem, you need to request a dump (if you don't have one already) and collect problem information to report to IBM.		
	To Get the Dump Output and Analysis Results:		
	Use the procedures described in these areas: 1) Obtaining a system dump, if you need to request a system dump. 2) Formatting a system dump. 3) Validating input.		
	d. See Searching for a matching problem.		
	e. See Chapter 3, "Reporting RACF problems to IBM."		
	4. If the prefix of one of the looping modules is neither ICH nor IRR , the problem was probably not caused by RACF. Note the prefixes of the looping modules. If the module is owned by IBM (modules owned by IBM usually start with the letters A through I, S, or X), see the diagnosis or logic document for the program that the module is a part of. To determine the name of the component that owns the module, use the component summary in <i>z/OS MVS Diagnosis: Reference</i> .		

Messages troubleshooting table

Table 8. Troubleshooting Table: Messages

Symptom	Recommended Procedures for Messages	
Messages with a prefix of IKJ	Description: These are TSO messages issued for RACF commands. IKJ messages are issued by the TSO Terminal Monitor Program (TMP).	
	Action	
	See z/OS TSO/E Messages for a description of the message and the condition causing it. Attempt to correct the problem from the information in the messages document.	
	2. If you cannot correct the problem from the information in the messages document, do the problem determination procedure related to the message.	

Messages

Table 8. Troubleshooting Table: Messages (continued)

Symptom	Recommended Procedures for Messages		
Messages with a prefix of ICH or	Description: These are RACF messages.		
İRR	Action		
	1. See <i>z/OS Security Server RACF Messages and Codes</i> for a description of the message and the condition causing it. Attempt to correct the problem from the information in <i>z/OS Security Server RACF Messages and Codes</i> .		
	2. If you cannot correct the problem from the information in <i>z/OS Security Server RACF Messages and Codes</i> , do the problem determination procedure related to the message.		
Messages with a prefix of BPX	Description: These are z/OS and OS/390 z/OS UNIX System Services messages.		
·	Action If there are no RACF messages with this message, the problem is probably not caused by RACF. See your system diagnosis guide for information on correcting this problem.		
Unnumbered messages	Description: Unnumbered messages are also issued by RACF.		
messages	Action		
	1. Make sure that any message IDs are included with the messages.		
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.		
	2. See <i>z/OS Security Server RACF Messages and Codes</i> for a description of the message and the condition causing it. Attempt to correct the problem from the information in the messages document.		
	3. If the message is not in <i>z/OS Security Server RACF Messages and Codes</i> , and you are certain it is a RACF message, see Documentation troubleshooting table.		

Performance problems troubleshooting table

Table 9. Troubleshooting Table: Performance Problems

Symptom	Recommended Procedures for Performance Problems		
Performance, such as:	Action		
 There is excessive I/O to the RACF database. Users report slow 	Most performance problems related to RACF are corrected by changing the way RACF is set up at an installation.		
response time, particularly when logging on or off, or when opening data sets.	Before suspecting that RACF itself is causing performance problems, review this checklist to assure that the problem is not actually caused by the way your installation has set up RACF. Pay close attention to any recent changes you have made in the way you have set up RACF. For more information about these performance considerations, see <i>z/OS Security Server RACF System Programmer's Guide</i> .		
	The rate at which users log on to TSO/E, sign on the IMS/VS or CICS/VS, or submit batch jobs on MVS affects system performance. The higher the rate, the lower the performance. You might see peaks and valleys in performance through the work day.		
	Using the RACLIST or GENLIST operands on the SETROPTS command can improve system performance.		
	Use of the global access checking table can improve system performance.		
	Using RACROUTE REQUEST=FASTAUTH instead of RACROUTE REQUEST=AUTH can improve system performance.		
	Using ADSP and PROTECT=YES can degrade system performance.		
	The processing performed by installation-written exit routines can affect system performance.		
	The placement of the RACF database on DASD (including how many DASDs the database is placed on) can affect system performance.		
	The use of logging by users with SPECIAL or group-SPECIAL attributes or users with AUDITOR or group-AUDITOR attributes can reduce system performance.		
	The gathering of resource statistics can reduce system performance.		
	• The use of certain RACF commands (such as SEARCH, LISTDSD with the ID or PREFIX operands, LISTGRP *, and others) can reduce system performance when there is a single RACF database.		
	The use of RACF utilities can reduce system performance when there is a single data set in the RACF database.		
	The use of erase-on-scratch can reduce system performance.		
Performance (continued)	During failsoft processing, the operator is prompted frequently, thereby degrading system performance while you repair RACF.		
	To improve system performance during failsoft processing, write a RACROUTE REQUEST=AUTH preprocessing exit.		
	List of groups processing can reduce system performance.		
	• Group authority processing when made to percolate for a user to subgroups owned by the group can reduce system performance.		
	 Defining many generic profiles within a data set high-level qualifier or a general resource class can hurt performance. 		
	The use of the IRRACEE VLF class can improve system performance. The use of the IRRUMAP, IRRGMAP, and IRRSMAP VLF classes can improve performance of z/OS and OS/390 z/OS UNIX System Services .		
	See Performing a preliminary search for a matching problem.		
	If you do not find a matching problem, you will need to collect problem information to report to IBM, using the procedures in the remainder of this list.		
	See Searching for a matching problem.		
	See Chapter 3, "Reporting RACF problems to IBM."		

RACF return codes troubleshooting table

Table 10. Troubleshooting Table: Return Codes

Symptom Recommended Procedures for Return Codes		
Return codes from	Action	
RACF macros (nonzero value in register 15)	1. For some macros, depending on the return code, there is a reason code in register 0. Check register 0 for this reason code. (To obtain the reason code from a RACF macro, see Obtaining RACF return codes and reason codes from a RACF macro invocation.)	
Togiotol Toy	2. See Utilities for a summary of some commonly encountered macro reason codes and advice on how to resolve problems that are due to an error in the program that issued a RACF macro. Note: Error return codes and reason codes from a RACF macro are generally due to a	
	problem in the program that issued the macro.	
	3. If you haven't done so already, look up the explanation of the RACF macro's return and reason codes. See z/OS Security Server RACF Macros and Interfaces, except for the RACROUTE macro, which is described in z/OS Security Server RACROUTE Macro Reference. Note: For the RACROUTE macro, you should also check the first and second words of the SAF parameter list. These are the return and reason codes from the RACF request (usually a RACF macro invocation).	
	4. Check whether any error messages were issued for the user request, and make sure that message IDs are included with the messages.	
	If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options: PROFILE WTPMSG MSGID.	
	5. The module that issued the macro is either owned by IBM or is a non-IBM product. If the module is owned by IBM (modules owned by IBM usually start with the letters A through I, S, or X), see the diagnosis or logic document for the program of which the module is a part. To determine the name of the component that owns the module. use the component summary in <i>z/OS MVS Diagnosis: Reference</i> .	
	6. If the problem still appears to be caused by RACF, use the diagnostic procedures described in these areas:	
	a. Performing a preliminary search for a matching problem. If you do not find a matching problem, continue diagnosis, using the procedures in the remainder of this list.	
	b. If you need to request a system dump, Obtaining a system dump.	
	c. Formatting a system dump.	
	d. Validating input.	
	e. Searching for a matching problem.	
	f. Chapter 3, "Reporting RACF problems to IBM."	
RACF manager	Action	
return codes	 See z/OS Security Server RACF Messages and Codes for a description of the message and the condition causing it. Attempt to correct the problem from the information in the messages document. 	
	2. If you cannot correct the problem from the information in the messages document, perform the problem determination procedure that is related to the message.	
Return codes from	Action	
RACF callable services	Check the parameter list for the SAF return code, the RACF return code, and the RACF reason code.	
	2. If you haven't done so already, look up the explanations of the return codes and reason codes. See z/OS Security Server RACF Callable Services and z/OS Security Server RACF Messages and Codes.	

Waits troubleshooting table

Table 11. Troubleshooting Table: Waits

Symptom F		Recommended Procedures for Waits		
Wait:		Action		
•	Enabled wait ("hang") in the task	1.	First, see your system diagnosis guide to check which module caused the wait. Try to find out what address space the module was running in.	
	that issued a RACF request		The key question to answer is, "Why was the job or user waiting?" (If a task is waiting for a RACF macro request, RACF might not have caused the wait; another routine	
•	Dummy (no work)		could cause the wait if it never released a resource needed by RACF.)	
•	wait Wait caused by RACF		Perform the remaining diagnostic steps only if you have determined that RACF is actually the cause of the problem (that is, RACF never released a resource or caused the wait in some other way).	
		2.	Check whether any error messages were issued for the user request that immediately preceded the wait. If a batch job produced the output, check that the job statement had MSGLEVEL=(1,1) specified. If a TSO/E user had the problem, check that the user profile had these options specified: PROFILE WTPMSG MSGID.	
		3.	If the prefix of a module that caused the wait is ICH or IRR, the problem is probably caused by RACF and these diagnostic procedures apply:	
			 Performing a preliminary search for a matching problem. If you do not find a matching problem, continue diagnosis, using the procedures in the remainder of this list. 	
			b. If you do not have a dump, Obtaining a system dump.	
			c. Formatting a system dump.	
			d. Validating input.	
			e. Searching for a matching problem.	
			f. Chapter 3, "Reporting RACF problems to IBM."	
		4.	If the prefix of the waiting module's name is neither ICH nor IRR , the problem was probably not caused by RACF. If the module is owned by IBM (modules owned by IBM usually start with the letters A through I, S, or X), see the diagnosis or logic document for the program of which the module is a part. To determine the name of the component that owns the module, use the component summary in <i>z/OS MVS Diagnosis: Reference</i> .	

Performing a preliminary search for a matching problem

Introduction to searching for a matching problem

This topic tells you how to create a list of symptoms for RACF. You (or IBM) can use these symptoms in the search argument for a preliminary search of a problem database.

A search argument consists of a set of problem symptoms, called search symptoms, to use in a search to identify a matching problem.

If you have a search tool such as Information/Management, consider searching these for a matching problem (which could have a fix already developed). You should search in the order shown:

- 1. PSP bucket (Preventive Service Plan)
- 2. Your problem database (if you have one)
- 3. An IBM problem database

If you find that the problem has already been reported, you can avoid or reduce time-consuming problem analysis work. In addition, if you have the Info/Access tool, or SoftwareXcel Extended in the ServiceLink application on IBMLink™, you can order the fix for the problem.

If you don't have a search tool, you need to collect additional search symptoms before you report the problem to IBM. (The troubleshooting tables list the additional procedures to use.)

If you are doing a structured search, you should provide symptoms in the order that they are listed in DAEDATA and SYMPTOMS output, in order to have the fastest search.

The procedure gives examples of the free-format search symptoms that you can use if you have a search tool such as Info/System (with the Info/MVS database) or Info/Management. It also has examples of the search symptoms that you need if you do a structured search using a tool such as Info/Management or Info/Access. You might need the structured symptoms if you call the IBM support center to report a problem or if you review the APAR and PTF descriptions in IBM's Early Warning System (EWS). EWS is on microfiche and on the Info/MVS database.

The formats used in the examples are the same formats that are used at the IBM support center to enter problem descriptions for APARs and to do searches.

Related information

If you need information about doing problem searches with the Info/System, Info/MVS, Info/Management, or Info/Access program, see Introducing the Information/Family.

For examples of Info/Management panels and structured search symptoms to use in a search for a matching problem, see Using Information/Family Problem Management.

Steps for searching for a matching problem

Before you begin: You need to verify that this is a problem caused by RACF and to collect some initial problem symptoms. See Troubleshooting tables for problems in RACF for steps to perform this prerequisite.

Perform these steps to:

- Make an initial list of search symptoms.
- 2. Use the list to search for a matching problem.
- 3. If you didn't find a match, try other symptoms.
- 4. If you found too many matches, add search symptoms.
- 1. Use Table 12 to select which search arguments apply to the type of problem you have.
- 2. Using Table 13 for examples of search arguments, do your first search for a match.
- 3. If your search doesn't produce a match, try widening your search.
 - a. Use the word "RACF" instead of the component ID.
 - b. Use fewer search arguments.

- 4. If a search produces too many matches, use some of the other symptoms listed in this procedure to narrow the search.
- 5. If your preliminary searches are unsuccessful, do the structured search described in Searching for a matching problem.
 - a. If a structured search is still unsuccessful, gather additional information before reporting the problem to IBM by using the diagnostic procedures recommended for your type of problem.
 - b. Return to where you were in the troubleshooting tables.
- 6. If your search has too many matches, consider using these procedures to add search symptoms:
 - a. Return to the troubleshooting tables to obtain one or more additional symptoms to narrow your search.
 - b. Obtain additional search symptoms by analyzing a dump or doing other in-depth analysis. (For lists of the procedures for doing the analysis, return to where you were in the troubleshooting tables.)

Note: Searching for a matching problem summarizes the additional symptoms that you can obtain through in-depth analysis.

You know you are done when you have found a problem match for your symptom or have contacted IBM for additional help.

Table 12. Preliminary Search Symptoms for RACF

Search Argument	Free-Format Example	Structured Example
Component identification (ID) The component ID matches problems that had RACF as either the cause of the problem or the apparent cause (for a problem that was reassigned to another component).	RACF 5752XXH00 5752SC1BN	PIDS/5752XXH00 PIDS/5752SC1BN
Release level of RACF: Use the FMID (function modification identifier). For a list of RACF FMIDs, see Table 14.	R902 or RI02 (R for release; I, the ninth letter of the alphabet, can stand for 9; and 02 for 02. R922 (for RACF 1.9.2) R210 (for RACF 2.1) R220 (for RACF 2.2) R230 (for FMID HRF2230) R240 (for FMID HRF2240) R260 (for FMID HRF2260) 2608 (for FMID HRF2608) 7703 (for FMID HRF7703)	LVLS/902 or LVLS/RI02 LVLS/922 LVLS/210 LVLS/220
RACF request that failed	RACHECK PROFILE	PCSS/RACHECK PCSS/PROFILE
Error reason code from the RACF request (if available)	rc00000004	PRCS/00000004

Table 12. Preliminary Search Symptoms for RACF (continued)

Search Argument	Free-Format Example	Structured Example
Associated error message ID The job log or system log might contain error messages associated with the problem that you encountered. Some problems produce multiple error messages, such as problems initiated by a previous abend or I/O error. General error messages, such as the IEA995I symptom dump message for all types of abends, aren't needed as search symptoms.	msglCH408I	MS/ICH408I
Associated reason code from message	rc04	PRCS/04
RACF module	ICHRIN00	RIDS/ICHRIN00
SMF record with error	SMF type 80	RECS/SMF80
Part of a document title	Security Administrator's Guide	PUBS/security PUBS/administrator's PUBS/guide
Symptoms for later searches		
Component ID of a service used by RACF, such as Master Scheduler If you suspect a problem in a system service used by RACF, consider a search argument of the service's component ID, plus the failing RACF request and the problem type (such as an abend and reason code).	5752SC1B8	PIDS/5752SC1B8
A PTF number Consider use of this symptom if a recent PTF (program temporary fix) updated a RACF module involved in the problem. This does not mean that an error exists in the PTF, only that the problem might occur after this PTF is installed.	UY00934 UW02010	PTFS/UY00934 PTFS/UW02010
Area within a document, such as a part, section, chapter, appendix, or page	Chapter3 appendixA	PUBS/CHAP3 PUBS/APPXA

Table 12. Preliminary Search Symptoms for RACF (continued)

Search Argument	Free-Format Example	Structured Example
Document order number	GC28-1154-01	PUBS/GC28115401
Document order numbers end with a version number, such as the 01 in GC28-1154-01. All version numbers are now two digits, although previously they could be one. You could leave off the second hyphen and the version numbers that follow it. Then, if you receive too many matches, add the version numbers to the search symptom.		

Examples of search arguments for RACF

Table 13 has examples of free-format search arguments for problems in RACF.

Table 13. Examples of Search Arguments for RACF

Problem Type	Example of Search Argument	Descriptions of Search Symptoms
Abend	5752XXH00	Component ID
	abend685	Abend code
	rc04	Abend reason code (if one exists)
Documentation error	5752XXH00	Component ID
	doc	The word doc
	RACHECK	The name of the RACF request with the documentation error
Incorrect output	5752XXH00	Component ID
	RACHECK	The type of output request that was involved
	output	The word <i>output</i>
Loop	5752XXH00	Component ID
	ICHRIN00	The name of any associated module (or RACF request)
	enabled loop	The word <i>loop</i> . Add the word <i>enabled</i> or <i>disabled</i> if you know the type of loop.
Message	5752XXH00	Component ID
	msgICH408I	The message identifier
	invalid password	Any inserted code (or text) in the message
Performance degradation	5752XXH00	Component ID
	RACHECK	The name of any associated RACF request
	performance	The word performance

Table 13. Examples of Search Arguments for RACF (continued)

Problem Type	Example of Search Argument	Descriptions of Search Symptoms
Return code from macro	5752XXH00	Component ID
	RACHECK	The return code and any reason code
	rc08rc04	(Specify both return code and reason code if a reason code occurred.)
Wait - hang or coded wait state (using ICHRIN00)	5752XXH00	Component ID
state (using form invoo)	ICHRIN00 enabled wait	The name of any associated RACF module (or RACF request)
		The word <i>wait</i> and any associated wait-state code (for a wait state indicated at the system operator's console). If you know the type of wait, add the word <i>enabled</i> , <i>disabled</i> , or <i>dummy</i> (for a no-work wait).
Wait - hang or coded wait state (using RACHECK)	5752XXH00	Component ID
state (using PAOLICON)	RACHECK wait03c	The name of any associated RACF module (or RACF request)
		The word <i>wait</i> and any associated wait-state code (for a wait state indicated at the system operator's console). If you know the type of wait, add the word <i>enabled</i> , <i>disabled</i> , or <i>dummy</i> (for a no-work wait).

Table 14. RACF FMIDs

RACF Level	RACF FMID
RACF 1.9	HRF1902
RACF 1.9.2	JRF1922
RACF 2.1	HRF2210
RACF 2.2	HRF2220
OS/390 Release 1	HRF2220
OS/390 Release 2	HRF2220
OS/390 Release 3	HRF2230
OS/390 Version 2 Release 4	HRF2240
OS/390 Version 2 Release 5	HRF2240
OS/390 Version 2 Release 6	HRF2260
OS/390 Version 2 Release 7	HRF2260
OS/390 Version 2 Release 8	HRF2608
OS/390 Version 2 Release 9	HRF2608
OS/390 Version 3 Release 10	HRF7703
OS/390 Version 3 Release 12	HRF7705
z/OS Version 1 Release 3	HRF7706
z/OS Version 1 Release 4	HRF7707
z/OS Version 1 Release 5	HRF7708
z/OS Version 1 Release 6	HRF7709
z/OS Version 1 Release 7	HRF7720

Table 14. RACF FMIDs (continued)

RACF Level	RACF FMID
z/OS Version 1 Release 8	HRF7730
z/OS Version 1 Release 9	HRF7740

Chapter 2. Collecting and analyzing problem data

This topic explains how to collect and analyze problem data. These tasks include obtaining dumps and traces, validating input, and searching for matching problems.

Collecting problem data

If you do not know what data to collect for the problem that you are diagnosing, see Troubleshooting the problem. Also, Chapter 3, "Reporting RACF problems to IBM" summarizes the information that you should consider collecting before reporting each type of problem to IBM.

Obtaining a description of a RACF installation

For advice on gathering information about a RACF installation, see the information on conducting an audit in *z/OS Security Server RACF Auditor's Guide*.

Obtaining a system dump

Prerequisites

You have a problem with an abend for which a system dump was not taken.

How to obtain a system dump

If the problem occurred while a batch job was using the DSMON command (or the RACF report writer), run the job again with a SYSABEND DD statement specified. This generates a system dump.

If an abend does not produce a system dump, and the problem is reproducible, set a SLIP trap to obtain a system dump the next time the problem recurs.

The trap set by this procedure causes an SVC dump to be generated. Generally, an SVC dump contains all the information needed for debugging RACF-related problems. You may want to re-create the problem you are investigating (or set up the conditions to allow the problem to recur) after setting the trap.

 On the operator's console, enter this command: SLIP SET, COMP=xxx, ACTION=SYNCSVCD, JOBNAME=jobname, END

where *xxx* is the system completion code and *jobname* is the job name (if a batch job is involved) or the user ID (if an interactive user is involved).

Note: For more information on setting the SLIP trap, see *z/OS MVS System Commands*.

2. When the abend occurs, the system console receives message IEA989I: SLIP TRAP ID=nnn MATCHED

where *nnn* is the system-assigned SLIP ID. The operator should notify you if a system dump was requested. You can format and read the system dump.

Note: A system dump is not generated if the SLIP is a NODUMP SLIP.

© Copyright IBM Corp. 1994, 2008

Formatting a system dump

Prerequisites

- IPCS
- A system dump (see Obtaining a system dump)

How to format a system dump

To start debugging a system dump, the IBM support center requires this information to be formatted in the dump.

- · Use IPCS to format the system dump by using:
 - SUMMARY
 - SUMDUMP
 - FORMAT
 - CURRENT
 - TRACE
 - LOGDATA
 - LPAMAP
 - CPUDATA
 - SYMPTOMS

This can help you start researching a problem. The IBM support center may request further information, for which other verbexits would be used for further research on specific problems.

Obtaining RACF return codes and reason codes from a RACF macro invocation

If the program that issued the RACF macro received an error return code from the macro, but did not produce a message containing the return and reason codes, you can use one of these techniques to obtain the codes:

- Use the RACF SET TRACE command. See Obtaining trace records using the SET TRACE command.
- Place a TSO TEST trap at the instruction after the macro expansion instructions in the program, and check the return and reason codes when the trap matches.

Note: You could use the SLIP command to set a trap, but it affects system performance. If you use SLIP, consider qualifying it with job name or PVTMOD options, and request an SVC dump when the trap is hit.

- Use the SPZAP ("superzap") service aid to modify the program that issued the RACF macro:
 - 1. Locate the RACF macro instruction in the assembly listing or the object code for the program.
 - 2. Use the SPZAP service aid to change the program's instruction that follows the last instruction of the macro expansion. Change the instruction operation (op) code to an invalid op code, such as X'00'.
 - 3. Re-create the problem, using JCL with a SYSMDUMP, SYSUDUMP, or SYSABEND DD statement. The invalid op code causes an X'0C1' abend. The SYSMDUMP DD statement is recommended if you plan to report the problem to IBM.

Obtaining RACF return codes and reason codes from a RACF callable service invocation

If the program that invoked the callable service received an error return code from the macro, but did not produce a message containing the return code and reason code, you can use one of these techniques to obtain the codes:

- Use the RACF SET TRACE command. See Obtaining trace records using the SET TRACE command.
- Place a TSO TEST trap at the instruction after the callable service invocation in the program, and check the return code and reason code when the trap matches.

Note: You could use the SLIP command to set a trap, but it affects system performance. If you use SLIP, consider qualifying it with job name or PVTMOD options, and request an SVC dump when the trap is hit.

- Use the SPZAP ("superzap") service aid to modify the program that invoked the callable service:
 - 1. Locate the callable service invocation in the assembly listing or the object code for the program.
 - 2. Use the SPZAP service aid to change the program's instruction that follows the callable service invocation. Change the instruction operation (op) code to an invalid op code, such as X'00'.
 - Re-create the problem, using JCL with a SYSMDUMP, SYSUDUMP, or SYSABEND DD statement. The invalid op code causes an X'0C1' abend.
 The SYSMDUMP DD statement is recommended if you plan to report the problem to IBM.

At the time of the trap or the 0C1 abend, Register 1 contains the address of the parameter list for the callable service. This parameter list contains the SAF return code and the RACF return code and reason code. See *z/OS Security Server RACF Callable Services* for more information.

Obtaining traces

When access to a resource is allowed (or denied) incorrectly, you can obtain more data about the problem with GTF trace. GTF trace must be activated to obtain trace output just before reproducing the problem.

To obtain a trace when access is incorrectly denied, do:

- To start GTF, enter this command: START GTF, TRACE=SLIP
- 2. Set this SLIP trap:

```
SLIP SET, IF, LPAEP=(ICHRFR00,0,0), ACTION=TRACE, JOBNAME=xxx, TRDATA=(STD, REGS, 1R??, +100), END
```

where xxx is the job name of a batch job or the user ID of an interactive user.

This SLIP trap produces a GTF trace entry each time a RACROUTE macro is invoked (ICHRFR00 is the module called by RACROUTE). The trace entry contains the parameter list passed with the RACROUTE macro request.

- 3. Use the START GTF command to trace the SVCs related to the RACHECK macro (equivalent to SVC 130) and RACDEF macro (equivalent to SVC 133). There is more than one way to do this. This is a suggestion only:
 - a. On the master console, enter the START GTF command with TRACE=SVCP specified.
 - b. When GTF prompts for trace-event keywords, specify SVC=(130,133).

Collecting data

- 4. Run the job that has the access problem (or ask the user to attempt to gain access to the resource again) while GTF is on.
- 5. Stop GTF after the job has ended or after the user has attempted access.
- 6. Examine the GTF trace output. See z/OS MVS IPCS Commands for more information.

Obtaining traces for program control and Program Access to Data Set (PADS) errors

Program control allows an installation to treat load modules (programs) as protected resources. This gives installations the ability to control who can execute which programs.

Load modules are protected by creating a profile for the program in the PROGRAM general resource class. A program protected by such a profile is called a controlled program.

An installation can use a controlled program as a condition for access to a specified data set. That is, some users can access specified data sets at a specified access level only while executing a certain controlled program. This is known as program access to data sets (PADS). PADS is set up by creating a conditional access list for the data set profile protecting the data sets.

In some cases, users trying to implement program control and PADS might receive message IEC1501I, ABEND 913-38, or message ICH408I, INSUFFICIENT ACCESS AUTHORITY, when they feel they have the necessary authority to open the data set through the conditional access list of the data set. In these scenarios, these error messages most commonly occur when a controlled program has loaded an uncontrolled program.

Other error messages will be generated when dealing with program control and PADS in the user's environment. These RACF processing messages can be used to diagnose errors when defining programs to RACF and the file system. Check the job log and security console for these diagnostic messages, and use the responses in z/OS Security Server RACF Messages and Codes to attempt to correct the problem before setting the slip traps.

In a RACF environment, a program and user combination can open a RACF-protected data set through conditional access list authority if all of the other programs in the environment are RACF-protected. RACF turns on a bit in the TCB, known as the "dirty bit" or TCBNCTL, to indicate that a program not protected by RACF has been loaded into the environment. If this bit is on, an uncontrolled program causes a failure. RACF provides an environment service, IRRENS00, to assist in handling program control and PADS. For more information on this service, refer to z/OS Security Server RACF Macros and Interfaces.

Thus, in a RACF environment, it is **not** sufficient to only protect the program doing the open of the data set. To correctly implement PADS, you must protect all of the programs loaded in the environment prior to the attempt to open the data set. This is also true for any utilities that are to be executed. If a utility loads another program during execution, this additional program must also be protected to prevent an error condition. To help users determine what programs need to be protected, a TRACE is provided in Trace examples so that when set correctly, it will print out the program name, data set name, and volume required to define profiles in the PROGRAM class for these other programs.

Attention

Read all of the information that follows before beginning any of the activities described.

Trace examples

This information provides two examples of traces. The first example writes a GTF trace record for each program loaded into the environment. The second example can determine additional programs that need to be protected.

Trace example 1: This slip should be used to write a GTF trace record for each program loaded into the environment:

SLIP SET, IF, ACTION=TRACE, LPAMOD=(ICHRFR00, xxxxx), J=jobname, TRDATA=(STD, REGS, zzzzzz), ML=100, END

The offset into ICHRFR00 where ICHRCP00 starts plus the yyy XXXXX

> value defined in Table 15 for your RMID level of the ICHRCP00 CSECT. Run an AMBLIST of ICHRFR00 to determine the offset of

the beginning of ICHRCP00 into ICHRFR00.

77777 See Table 15 for the correct TRDATA information based on your

RMID level of the ICHRCP00 CSECT. The yyy and zzzzz values specified for UW21213 should be used for all later RMID levels beginning with RACF 2.2.0, and for the OS/390 Release 3 level of RACF (HRF2230). If you have a later RMID level for RACF 2.1.0,

you should use the yyy and zzzzz values specified for UW16891.

If the program is executed in batch, this is the name of the job that jobname

> executes the program. If a TSO user executes the job, this is the TSO user ID. In the case of a TSO user ID, you must set the slip

prior to the user logging on to the system.

Table 15. RMID Levels, yyy and zzzzz Values for Example 1

RMID LEVEL	ууу	ZZZZZ
UW03221	406	9R?+A0?,+7,9R?+A4?,+2B,9R?+A8?,+5
UW08914	406	9R?+A0?,+7,9R?+A4?,+2B,9R?+A8?,+5
UW16891	вс	9R?+A0?,+7,9R?+A4?,+2B,9R?+A8?,+5
HRF2220	5E	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
UW21213	60	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
HRF2240 to HRF2608	80	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
HRF7703	84	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
HRF7707	9C	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5

Because this slip produces GTF records, you need to start GTF ensuring that you use PARM TRACE=SLIP, then use IPCS to format the data with the GTFTRACE IPCS command.

If the preceding steps have been implemented correctly, 'SLIP S+U' entries are generated in the trace records. Under the 'SLIP S+U' heading, locate the 'General Purpose Register Values' line and obtain the value of R15 for each of the 'SLIP S+U' records in the trace output.

Collecting data

R15 can have 5 possible values:

- User or group is authorized to resource.
- 4 Resource is not defined to RACF.
- 8 User or group is not authorized to resource.
- C Resource is not defined to RACF and library is controlled.
- 10 User or group is authorized to resource and program has NOPADCHK attribute.

If the value in R15 is 4, 8, or C, a profile in the PROGRAM class must be defined to protect the program identified by this trace entry. In addition to defining the profile in the PROGRAM class, the PERMIT command must be issued to put users or groups in the access list for program's profile. To rebuild the in-storage profile list, issue the SETROPTS WHEN(PROGRAM) REFRESH command after making changes to the PROGRAM class. This allows the changes to take effect immediately. For more information on defining profiles in the PROGRAM class and creating entries in a conditional access list, refer to z/OS Security Server RACF Security Administrator's Guide.

Note: If the RACF database is being shared with other systems, the SETROPTS REFRESH takes effect only on the system on which it was issued. In this case, the SETROPTS WHEN(PROGRAM) REFRESH must be issued on all the other sharing systems. This allows the PROGRAM class changes to take effect immediately on the other systems as well. An exception occurs when RACF is enabled for sysplex communications.

The information that you need to define the PROGRAM class profile correctly is found in the 'SLIP USR' of the trace record following the 'SLIP S+U' information. If the zzzzz value was set correctly you will see:

```
0008 PROGRAM
002C DATASET.NAME
0006 VOLUME
```

where:

PROGRAM

Is the actual name of the program being loaded as it is known to RACF.

DATASET.NAME

Is the name of the data set from which the program name was loaded. There are instances where the library name does not show up in the trace.

VOLUME

Is the volume that the data set resides on.

Note: As stated in z/OS Security Server RACF Security Administrator's Guide, if a TSO user has executed a non-controlled program during the current session. and then attempts to access a PADS data set, the attempt fails. The TSO user can in some cases temporarily regain a controlled environment by invoking the controlled program through the TSOEXEC command. See Special consideration when REXX is involved for exceptions to this. When writing a program, you can do the equivalent by invoking the TSO IKJEFTSR service. This technique can prove extremely useful to users who want to have their programs run from the TSO session, but do not want to protect every program that is executed between logon time and execution of the program intended to access the data set.

Also, program AAOEFTB3 might require protection if the MVS/TSO Dynamic Steplib Facility, program number 5798-DZW, is used while attempting to implement program control in the environment created by TSOEXEC. AAOEFTB3 is normally found in SYS1.LINKLIB.

Trace example 2: There are instances in which the SLIP trace specified in Trace example 1 might not catch all the modules that should be protected. This SLIP should be used in conjunction with the SLIP trace in Trace examples if you're still failing with an ABEND 913.

With this trap, it is not necessary to check the value in general register 15. All modules that appear in the trace records need to be protected.

Note: The same module name might appear multiple times in the trace output. Also, you might not see a library name in the trace.

To determine the additional programs that need to be protected use:

SLIP SET,IF,ACTION=TRACE,LPAMOD=(ICHRFR00,xxxxx),J=jobname,
TRDATA=(STD,REGS,zzzzz),END

RMID LEVEL	ууу	ZZZZZ
UW03221	8A8	9R?+A0?,+7,9R?+A4?,+2B,9R?+A8?,+5
UW08914	8E4	9R?+A0?,+7,9R?+A4?,+2B,9R?+A8?,+5
UW16891	D2	9R?+A0?,+7,9R?+A4?,+2B,9R?+A8?,+5
HRF2220	76	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
UW21213	78	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
HRF2240 to HRF2608	98	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
HRF7703	9C	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5
HRF7707	B4	9R?+00?,+7,9R?+04?,+2B,9R?+08?,+5

As with the previous TRACE, you need to run an AMBLIST of ICHRFR00 to determine the offset of ICHRCP00. Also, GTF must be started with TRACE=SLIP.

Special consideration when REXX is involved

As mentioned previously, the TCB contains a bit that indicates if the current environment is trusted to open a program accessed data set (PADS) or not. This bit, the TCBNCTL, is turned on by RACF when an unprotected and "untrusted" program is loaded into the environment.

The TCB dirty bit can also be turned on by TSO/E itself. If this is the case, none of the RACF traces will catch this. If you issue TSOEXEC pgm_name, which called IRXINIT to create a REXX[™] environment, TSO/E would mark the TCBs on the parallel side "dirty", if the job-step TCB is "dirty". If there are any stack-related commands in the REXX exec, TSO/E checks the job-step TCB and marks the parallel side dirty if the job-step dirty bit is on. Examples of stack-related commands are: PUSH, PULL, QUEUE, MAKEBUF.

Even though TSOEXEC creates a "clean" parallel side in a TSOE address space, TSOE can mark the parallel side "dirty" if the REXX exec is being used and depending on what REXX is doing.

Special consideration when using IMS

DFSDLOC0 is an IMS[™] module that issued an OPEN. This module is not loaded through Contents Supervisor in which case RACF is not called. You cannot use PROGRAM CONTROL/PADS if DFSDLOC0 is involved.

Obtaining traces on z/OS UNIX System Services

When access to a resource is allowed (or denied) incorrectly, you can obtain more data about the problem by using the RACF SET TRACE command, or with GTF trace. GTF trace must be activated to obtain trace output just before reproducing the problem.

To obtain a trace when access is incorrectly denied, using the RACF SET TRACE command. See Obtaining trace records using the SET TRACE command.

To obtain a trace with GTF trace, the trace must be activated to obtain trace output just before reproducing the problem. You may use this procedure:

1. To start GTF, enter this command: START GTF, TRACE=SLIP

2. Set this SLIP trap for callable services:

```
SLIP SET, IF, LPAEP=(IRRRFR10,0,0), ACTION=TRACE, JOBNAME=xxx,
     TRDATA=(STD, REGS, 1R?, +100), END
```

where xxx is the job name of a batch job or the user ID of an interactive user. This SLIP trap produces a GTF trace entry each time a RACF callable service is invoked (IRRRFR10 is the module called by the RACF callable service). The trace entry contains the parameter list passed with the RACF callable service request.

- 3. Run the job that has the access problem (or ask the user to attempt to gain access to the resource again) while GTF is on.
- 4. Stop GTF after the job has ended or after the user has attempted access.
- 5. Examine the GTF trace output. See z/OS MVS IPCS Commands for more information.

Obtaining information about z/OS UNIX file and directory violations

An error occurs when RACF detects an attempt to specify a z/OS UNIX function for which the user does not have authority. When an ICH408I message is issued, it contains a syscall-name which identifies the z/OS UNIX callable service that invoked RACF. In some cases, the message indicates that you do not have sufficient authority to perform the callable service because it requires superuser authority. Superuser authority is UID 0, or authority to an appropriate FACILITY class or UNIXPRIV class profile. In other cases, the message indicates that you do not have access to a file or a directory, and contains your access intent and allowed access.

These message indicates that you do not have permission to find the file pointed to by path name /u/myuser/path:

```
ICH408I USER(MYUSER ) GROUP(MYGROUP ) NAME(ME)
/u/myuser/path CL(DIRSRCH) FID(01C7C3E6E5D4E400011E000000000)
INSUFFICIENT AUTHORITY TO LOOKUP
ACCESS INTENT(--X) ACCESS ALLOWED(GROUP ---)
EFFECTIVE UID (0000000023) EFFECTIVE GID (0000000012)
```

The final line of the message indicates the UID and GID upon which RACF has based its decision. The first thing to verify is that the UID and GID are the expected values for the failing user ID. In some cases, the values may not correspond to the actual user ID which performed the function (identified within the message). For example, if you execute a set-uid file, which runs under the authority of the file owner, the UID displayed will be the file owner. In this case, it is the file owner, and not the end user, who lacks authority to the file or directory.

In the message, a syscall-name of LOOKUP or OPEN, a class name of DIRSRCH, and an access intent of X are all indicators that you do not have authority to a directory in the path name.

This lists the permissions encoded by the file permission bits:

r- Read permission

Are you allowed to read the file/directory?

w - Write permission

Are you allowed to write to the file/directory?

x - Execute permission

Are you allowed to execute the file?

x - Lookup permission

Are you allowed to traverse the directory?

Correcting the permissions when access is denied

To correct the permissions, you should do:

 Verify that every directory contained in the path has the execute permission bit set.

Examine the path printed in the message. For every intermediate directory, including the root, issue the command:

```
ls -alLd directory-name
```

If the path is: /a/b/c, the commands are:

```
ls -alLd /
ls -alLd /a
ls -alLd /a/b
ls -alLd /a/b/c
```

Verify that the execute bits are set by examining the output of those commands and correct, if necessary.

```
chmod +x filename
```

Note: After granting this permission, another ICH408I message may be generated, which although similar, is different in the file ID.

• Use the file ID (FID) printed in the message to determine the exact directory which needs to have permission granted.

Obtain the auditid tool, which will search the file system for a particular file ID contained in the message. The auditid tool can be found on the z/OS UNIX System Services Tools and Toys web site http://www.ibm.com/servers/eserver/zseries/zos/unix/bpxa1toy.html.

List the directory using this command:

```
ls -alLd directory-name
```

Verify that the execute bits are set by examining the output of this command and correct, if necessary.

```
chmod +x filename
```

Repeat, if necessary, until there are no more violations.

See z/OS UNIX System Services Programming: Assembler Callable Services Reference for more information on syscall functions or z/OS UNIX System Services Planning for setting up security for files and directories.

Obtaining trace records using the SET TRACE command

The SET TRACE(APPC | NOAPPC | ASID | NOASID | CALLABLE | NOCALLABLE | DATABASE | NODATABASE | IMAGE | NOIMAGE | JOBNAME | NOJOBNAME | CALLABLE | NOCALLABLE | RACROUTE | NORACROUTE) command specifies whether or not Generalized Trace Facility (GTF) records should be created for the specified events. If the TRACE operand is specified, at least one suboperand is required. The record created is EF44 for each trace event. See z/OS MVS IPCS User's Guide or z/OS MVS Diagnosis: Tools and Service Aids for information on viewing these records.

Note: These records are intended only for diagnosis use when requested by the IBM support center. The format will not be documented.

Attention

Trace records might contain passwords and therefore, trace output data sets should be appropriately protected.

Command tracing

Command tracing can be useful when diagnosing command errors and can be used with any command in z/OS Security Server RACF Command Language Reference that supports the AT keyword. It provides a step-by-step history of how the command text is parsed and rebuilt by the RACF command envelope module and can be used to determine which TSO macros are used. It can help determine if the problem is in the command envelope module or the command processor load module and also determine where a failure occurred during command parsing and rebuilding.

To obtain a command trace, do:

- 1. At the operator console, activate SET TRACE(IMAGE).
- 2. From a TSO terminal in TSO READY mode or from ISPF Option 6 (Command), do one or more of:
 - Issue a RACF command and append the two characters -c (note there's a leading blank between the command and the two characters) to obtain a trace of the command buffer. This keyword is the most useful and is recommended over the others.
 - Issue a RACF command and append the two characters -t (note there's a leading blank between the command and the two characters) to obtain a trace of the TSO macros used during the parsing of the RACF command and to obtain a trace of the command buffer.
 - Issue a RACF command and append the two characters -n (note there's a leading blank between the command and the two characters) to not run the command.
- 3. Output is sent to the user's TSO terminal.

Notes:

- 1. The three characters that are added to the end of the command must be entered exactly as shown and in lowercase letters only. That is, the command image must be followed by one blank space, either -c, -t, or -n and no trailing blanks.
- 2. Each of these keywords does one thing, but can be issued on the same command together to get multiple results. For example, -c -n would trace, but not run the command.
- 3. If you front-end commands, ensure that theis information about the command buffer is passed to RACF:
 - The command alias name (for example, AG, ADDGROUP, and so on) is still the first thing in the buffer
 - The -c, -t, and -n are the last characters in the buffer (with no trailing blanks).
- 4. Do not use the common command exit, IRREVX01, to put trace characters in the command buffer. Doing this causes a parse error.

See Front-ending RACF commands for additional information on front-ending RACF commands.

Example of command tracing: Command tracing would be helpful in this example. You entered the command, *ALTUSER MURPHY DATA('PRESIDENT - CATSKILL DIVISION')*, and the command seemed to run, but the installation data field was not updated. By reissuing the command with the *-c* appended to the end of it, *ALTUSER MURPHY DATA('PRESIDENT - CATSKILL DIVISION') -c*, (note the leading blank between the command and the two characters) you can quickly determine if the RACF command envelope module parsed and rebuilt the command image properly before invoking the ALTUSER command processor module.

The command envelope module does multiple parses and rebuilds of the RACF command. If the traced image has the correct installation data, the problem exists in the command processor or some deeper level of RACF. If the traced image does not have the correct installation data, you isolated the problem to the command envelope module.

Figure 1 shows the command:

ALTUSER MURPHY DATA('PRESIDENT - CATSKILL DIVISION') -c

being issued, traced, and rebuilt correctly with all the proper keywords. Therefore, the problem must exist in the command processor or some deeper level of RACF.

```
IRRV099I <ALU>
IRRV099I <ALU>
IRRV099I <ALU>
IRRV099I <ALU
IRRV099I <ALU
                    (MURPHY>
IRRV099I <ALU
                    (MURPHY)>
IRRV099I <ALU
                    (MURPHY)>
IRRV099I <ALU
                    (MURPHY) DATA>
IRRV099I <ALU
                    (MURPHY) DATA(>
IRRV099I <ALU
                    (MURPHY) DATA('>
IRRV099I <ALU
                    (MURPHY) DATA('PRESIDENT - CATSKILL DIVISION>
                    (MURPHY) DATA ('PRESIDENT - CATSKILL DIVISION'>
IRRV099I <ALU
                    (MURPHY) DATA('PRESIDENT - CATSKILL DIVISION'>
IRRV099I <ALU
IRRV099I <ALU
                    (MURPHY) DATA ('PRESIDENT - CATSKILL DIVISION' )>
IRRV099I <ALU>
IRRV099I <ALU>
IRRV099I <ALU>
IRRV099I <ALU
                    (MURPHY>
IRRV099I <ALU
IRRV099I <ALU
                    (MURPHY)>
IRRV099I <ALU
                    (MURPHY)>
IRRV099I <ALU
                    (MURPHY) DATA>
IRRV099I <ALU
                    (MURPHY) DATA(>
IRRV099I <ALU
                    (MURPHY) DATA('>
                    (MURPHY) DATA('PRESIDENT - CATSKILL DIVISION>
IRRV099I <ALU
                    (MURPHY) DATA ('PRESIDENT - CATSKILL DIVISION'>
IRRV099I <ALU
                    (MURPHY) DATA('PRESIDENT - CATSKILL DIVISION'>
IRRV099I <ALU
IRRV099I <ALU
                    (MURPHY) DATA('PRESIDENT - CATSKILL DIVISION' )>
```

Figure 1. Trace Output Showing a Problem in the Command Processor or RACF

Tracing the R admin callable service

RACF provides a component trace ability for the R admin callable service. To activate this trace, start GTF specifying TRACE=USR, and issue the RACF SET TRACE(IMAGE) command. When tracing of IMAGE events is active, the R_admin callable service records a snapshot of the input data it receives in GTF records, including:

- The function-specific parameter list containing segment and field data
- · The caller's jobname, ASID, PSW, and ASCB address

It also logs, in a separate record:

- The return code
- The reason code
- · The output messages

Tracing the Callable Services, RACROUTE, and RACF Database Manager Request calls

RACF provides a trace facility that will allow tracing Racroutes, Callable Services, and RACF Database Manager Requests. When tracing these services, the trace routine will copy the parameter lists into a GTF record before and after the function executes. IPCS is used to view the trace data. To obtain these traces:

- 1. Start the GTF using the GTFRACF Figure 2 or other procedure: START GTFRACF.GTF,,,NOPROMPT
- 2. Use the SET command to enable your trace: @SET TRACE(RACROUTE(TYPE(5)) JOBNAME(IBMUSER))
- 3. Reproduce the scenario that you desire. For example start batch job, login, start application, use CICS® application or access resource.

- Next stop GTF to prevent excessive traces: STOP GTF
- 5. Use IPCS to view the trace data. The input trace data is contained in the dataset specified on the IEFRDER DD card in the GTFRACF (or other) procedure. The sample GTFRACF procedure specifies 'SYS1.TRACE'. Once the TSO IPCS session is active the IPCS subcommand 'IP GTF USR' may be used to display the formatted trace.

Note: The SET TRACE command sets data in the IRRSAFT control block, see Appendix B, "The Security Product Trace Area (SAFT)." This information can be used by IBM support to help diagnosis SAF TRACE problems.

Performance Considerations:

• Security as implemented on the OS/390, z/OS platform includes many calls to the security product. This trace facility can adversely affect system performance by adding to the path length associated with performance sensitive security functions. This trace should only be used as a debugging aid. Caution should be exercised when designing the trace (as with any other trace) so as to impose the least performance penalty. For example, if the address space ID or jobname is known, use these to restrict the scope of the trace.

Usage hints:

- RACF database contention
 - The scope of RACF database serialization is dependent on the RACF database manager parameter list. Set up a trace for Manager ALTER requests on the specific ASID indicated via GRS contention displays. Examine the trace records to find out what RACF is changing in the database so frequently.
 - When applications specify subsystem and requestor information, this will be contained in the trace record header. You can determine who is issuing the security function.

Figure 3. Sample Parmlib Member: GTFPRM#O

Reading a trace output: The trace output formatted by IPCS is split into 3 main areas. The first area contains common information for all services. For example, the caller's information and return codes. The parameter lists and unloaded parameters are found in the second area. The third area is a complete hex dump of the entire GTF record which includes the header information, parameter lists and all of the parameters that were unloaded.

For RACROUTE requests' there are two parameters lists. The first one is the SAF parameter list mapped by ICHSAFP. The second parameter list is mapped by the specific RACROUTE type parameter list. These are described in z/OS Security Server RACF Data Areas. The parameter lists for Callable Services can be found in z/OS Security Server RACF Callable Services. For Manager calls, see the Diagnosis Guide for the Manager parameter list mapping.

Following the parameter lists are the parameters that are unloaded. Not all parameters are unloaded. Before most parameters are unloaded, there are extra entries that say OFFSET##. This is for informational purposes to let you know that the following parameter is at offset ## in the parameter list. This helps determine what parameter you are examining.

Due to nesting of some services PRE and POST trace records might not be in sequential order. For example, one might see two PRE calls and then two POST calls.

Explaining trace header information:

Trace identifier

SAFTRACE Record type 54.

Record eyecatcher

Eyecatcher for the SAFTRACE record type: RTRACE.

Trace type

Identifies what trace this is. Types are OMVS for callable services, MNGR for manager calls, or RACF for RACROUTE traces. These types are followed by PRE or POST to indicate the record pertains to a pre-function trace or post-function trace.

Ending sequence

This will contain a unique identifier in the case of the trace record exceeded the maximum size. In case of an abend during the trace, it will contain RECOVERY. Ending sequences indicate a problem occurred during trace capture. If you find these, it is indicative of a problem with the parameter list built by the caller of the function.

Calling address

Address of the caller. This is useful along with a dump of the address space when determining the caller of the service in question. It may not be possible to determine the caller of the function using the Request/Subsystem (when available).

Requestor/Subsystem

Caller's SAFPREQR and SAFPSUBS as specified on RACROUTE.

Primary jobname

Primary jobname.

Primary asid

Primary ASID.

Primary ACEEP

Primary ASID related ACEE pointer, as indicated in ASXBSENV.

Home jobname

Home Jobname.

Home asid

Home ASID.

Home ACEEP

Home ASID related ACEE pointer as indicated in the home address space ASXBSENV field.

Task address

TCB pointer of current task.

Time Time stamp.

Error class

Possible Security product resource class name in error.

Service number

Service number for Callable service or RACROUTE. (See Table 17 and Table 18 for supported services).

RACF Return code

RACF Return Code.

RACF Reason code

RACF Reason Code.

Return area address

Address of data returned by the function. When used in conjunction with a dump of an address space, storage creep problems can be isolated to the application.

Parameter count

Number of parameters that were captured. Note, this is not the number of parameters in the parmlist, but rather the number of parameters which were collected.

Tables:

Table 17. Callable services type numbers

CALLABLE SERVICE	Service Number or TYPE (HEX)	Service Number or TYPE (DECIMAL)
IRRSIU00	1	1
IRRSDU00	2	2
IRRSMF00	3	3
reserved	4	4
IRRSMM00	5	5
IRRSKA00	6	6
IRRSKP00	7	7
IRRSUM00	8	8
IRRSGM00	9	9
IRRSGG00	A	10
IRRSSU00	В	11
IRRSEU00	С	12
IRRSSG00	D	13
IRRSEG00	E	14
IRRSCO00	F	15
IRRSCF00	10	16
IRRSCA00	11	17

Table 17. Callable services type numbers (continued)

IRRSEX00		18
IRRSAU00	12 13	19
	14	
IRRSKO00		20
IRRSQS00	15	21
IRRSQF00	16	22
IRRSCS00	17	23
IRRSKF00	18	24
IRRSMR00	19	25
IRRSPT00	1A	26
IRRSUG00	1B	27
IRRSFK00	1C	28
IRRSM100	1D	29
IRRSK100	1E	30
IRRSC100	1F	31
IRRSC200	20	32
IRRSGE00	21	33
IRRSD100	22	34
IRRSDK00	23	35
IRRSUD00	24	36
IRRSDA00	25	37
IRRSIA00	26	38
IRRSEQ00*	27	39
IRRSIM00	28	40
IRRSDL00	29	41
IRRSMK00	2A	42
IRRSPK00	2B	43
IRRSPX00	2C	44
IRRSCH00	2D	45
IRRSPY00	2E	46
IRRSCL00	2F	47
IRRSSB00	30	48
IRRSWP00	31	49
IRRSGS00	32	50
IRRSAX00	33	51
IRRSGI00	34	52

Note: Callable Service IRRSEQ00, R_Admin, has its own trace facility.

Table 18. RACROUTE CALL= service type number

RACROUTE CALL=	Service / Type Number in Hex	Service / Type Number in Decimal
AUTH	1	1

Table 18. RACROUTE CALL= service type number (continued)

RACROUTE CALL=	Service / Type Number in Hex	Service / Type Number in Decimal
FASTAUTH	2	2
LIST	3	3
DEFINE	4	4
VERIFY	5	5
EXTRACT	6	6
DIRAUTH	7	7
TOKENMAP	8	8
VERIFYX	9	9
TOKENXTR	A	10
TOKENBLD	В	11
EXTRACT, BR=YES	С	12
AUDIT	D	13
STAT	Е	14
SIGNON	F	15
TOKENMAP, XMEM	10	16
TOKENXTR, XMEM	11	17

Examples of trace output: When an ACEE is dumped in the trace record, the associated ACEX, USP, and TOKEN are also dumped with it.

Callable Service: This is an example of SAF trace output for the R_dceauth Callable Service (service type 37) PRE and POST entries.

```
**** GTFTRACE DISPLAY OPTIONS IN EFFECT ****
USR=ALL
**** GTF DATA COLLECTION OPTIONS IN EFFECT: ****
USRP option
        **** GTF TRACING ENVIRONMENT ****
    Release: SP7.0.3 FMID: HBB7706 System name: RACFR13
    CPU Model: 4381 Version: FF Serial no. 111515
USR57 F44 ASCB 00FA9500
                                JOBN J23DC002
```

Following is a formatted R TRACE record. This trace record was generated by IRRTRC00 with IDENT(R_TRACE).

T T	0000000		
Trace Identifier:	00000036		
Record Eyecatcher:	RTRACE		
Trace Type:	OMVSPRE		
Ending Sequence:			
Calling address:	00000000	8B000BAE	
Requestor/Subsystem:			
Primary jobname:	J23DC002		
Primary asid:	0000012E		
Primary ACEEP:	00000000	006F6700	
Home jobname:	J23DC002		
Home asid:	0000012E		

Home ACEEP:	
Service number: 00000025 RACF Return code: 00000000 RACF Reason code: 00000000 RACF Reason code: 00000000 RACF Reason code: 00000000 00000000 00000000 Return area address: 00000000 Area length: 00000000 Area value: 080016EC 080016F4 080016EC 080019A1 080019C5 080019F9 080019F9 080019F2 0800019F2 080019F2 0800019	
Area value: 0B001B2C 0B0016EC 0B0016F0 0B0016EC 0B0016F4 0B0016EC 0B0016F8 0B001700 0B0016EC 0B0019F1 0B0019C5 0B0019E9 0B0019F2 0B0019F2 0B001AE8 0B001704 0B001706 0B0019F2 0B0019F2 0B001AE8 0B001704 0B001706 0B001706 0B0019F2 0B0019F2 0B001AE8 0B001704 0B001706 0B001706 0B0019F2 0B0019F2 0B001AE8 0B001704 0B001706 0B000008 0B001706 0B0000008 0B0000000 0B0000000 0B0000000 0B0000000	
0B001B2C 0B0016FC 0B0016FC 0B0016FC 0B0016FC 0B0016FC 0B001700	
Area value: D6C6C6E2 C5E30004 OFFSET Area length: 00000004 Area value: 00000000 Area length: 00000008 Area value: D6C6C6E2 C5E30008 OFFSET Area length: 00000004 Area value: 00000000 Area value: 00000000 OFFSET Area length: 00000008 Area value: D6C6C6E2 C5E3000C OFFSET Area length: 00000004 Area value: 00000000 Area length: 00000008 Area value: 00000000 OFFSET Area length: 00000008 Area value: D6C6C6E2 C5E30010 OFFSET Area length: 00000004 Area length: 00000004 Area value: 00000000 Area length: 000000004 Area value: 000000000 Area length: 000000008 Area value:	Z
D6C6C6E2 C5E30004 OFFSET. Area length: 00000000 I Area value: 000000008 I Area value: 06C6C6E2 C5E30008 I OFFSET. Area length: 00000004 I Area value: 00000008 I Area value: 00000008 I OFFSET. Area value: 00000004 I Area value: 00000004 I Area value: 00000008 I Area value: 00000008 I Area value: 00000004 I Area value: 00000004 I Area value: 00000000 I Area length: 00000004 I Area value: 00000000 I Area length: 00000000 I Area length: 00000000 I Area value: 00000000 I	
Area value: 00000000	I
00000000 Area length: 00000008 Area value: 066666E2 C5E30008 OFFSET Area length: 00000004 Area value: 000000008 Area value: 066666E2 C5E3000C OFFSET Area length: 00000004 Area value: 00000000 Area value: 066666E2 C5E30010 OFFSET Area value: 00000004 Area length: 00000004 Area value: 000000004 Area length: 000000004 Area value: 000000008 Area length: 000000008 Area value:	
Area value: D6C6C6E2 C5E30008 OFFSET Area length: 00000004 Area value: 000000000 Area length: 00000008 Area value: D6C6C6E2 C5E3000C OFFSET Area length: 00000004 Area value: 00000000 Area value: D6C6C6E2 C5E30010 OFFSET Area value: D6C6C6E2 C5E30010 OFFSET Area value: D6C6C6E2 C5E30010 OFFSET Area value: 000000000 Area value: 000000000 Area value: 000000000 Area value:	I
D6C6C6E2 C5E30008 OFFSET Area length: 000000004 Area value: 000000008 Area value: 000000008 Area value: 000000004 Area length: 000000004 Area value: 000000008 Area value: 000000008 Area length: 000000004 Area length: 000000004 Area value: 000000004 Area value: 000000008 Area length: 000000008 Area value: 000000008	
Area value: 000000000	I
00000000 Area length: 00000008 Area value: 06C6C6E2 C5E3000C 0FFSET Area length: 00000004 Area value: 000000008 Area length: 00000008 Area value: 00000004 Area length: 00000004 Area value: 000000004 Area value: 000000008 Area length: 000000008 Area value: 000000008	
Area value: D6C6C6E2 C5E3000C OFFSET Area length: 00000004 Area value: 00000000 Area length: 00000008 Area value: D6C6C6E2 C5E30010 OFFSET Area length: 00000004 Area value: 00000000 Area value: 000000000 Area value:	1
D6C6C6E2 C5E3000C OFFSET Area length: 00000004 Area value: 00000000 Area length: 00000008 Area value: D6C6C6E2 C5E30010 OFFSET Area length: 00000004 Area value: 00000000 Area length: 00000008 Area value: 000000000	
Area value: 000000000 Area length: 00000008 Area value: D6C6C6E2 C5E30010 OFFSET Area length: 00000004 Area value: 00000000 Area length: 00000008 Area value:	I
00000000 Area length: 00000008 Area value: OFFSET Area length: 00000004 Area value: Area length: 00000008 Area value:	
Area value: D6C6C6E2 C5E30010 OFFSET Area length: 00000004 Area value: 000000000 Area length: 00000008 Area value:	I
D6C6C6E2 C5E30010 OFFSET Area length: 00000004 Area value: 00000000 Area length: 00000008 Area value:	
Area value: 000000000 Area length: 00000008 Area value:	I
00000000 Area length: 00000008 Area value:	
Area value:	I
DOCOCOEZ CSESOO14 OFFSET	I
Area length: 00000004	

Area valu 00000000	ie:				
Area leng	ıth:		80000008		
Area valu D6C6C6E2	ne: C5E30018			OFFSET	
Area leng	th:		00000004		
Area valu 00000000	ie:			····	
Area leng	th:		80000008		
Area valu D6C6C6E2	c5E3001C			OFFSET	
Area leng	th:		00000004		
Area valu 7FFF5268	ie:			"	
Area leng	ith:		000000A8		
Area valu C1C3C5C5 00000000 E2F14040 40404040 0000000 0000000 0000000 000000	FF0000A8 05C8D6D5 40400101 00000000 40404040 00000000 7FFD3258 00A00000 00000000 7FFD3968	02000000 C4C14040 0001054F 0000000 0000000 40404040 00000000 000000	0000000 4004E2E8 40404040 00000000 00000000 40404040 0101054F 00000000 00000000	ACEEyHONDA .SY	
Area leng	ıth:		00000050		
Area valu 50010000 00000000 00000000 00000000 C8D6D5C4	0000C000 00000000 0000000 0000000 C1404040	00000000 00000000 00000000 00000000 E2E8E2F1	00000000 00000000 00000000 00000000 40404040	&{	
Area leng	th:		00000090		
Area valu C1C3C5E7 00000000 00000000 00000000 00000000 0000	03000000 00000000 000000024 00000000 00000000	00000000 00000000 7FFD3000 00000000 00000000 00000000 00000000	00000000 00000000 00000000 00000000 0000	ACEX	
Area length:			00000008		
Area valu D6C6C6E2	c5E30020			OFFSET	
Area leng	th:		00000004		
Area valu	ie:				

00000000			••••	
Area length:	80000008			
Area value: D6C6C6E2 C5E30024			OFFSET	
Area length:	00000024			
Area value: 81828384 85868182 838460F1 F1818160 F4F5F4F5	86608182 F4F5F4F5		abcdefab-cdef-ab cd-11aa-45454545 4545	
Area length:	80000008			
Area value: D6C6C6E2 C5E30028			OFFSET	
Area length:	00000024			
Area value: 81828384 85868182 F3F260F1 F1818160 F4F5F4F5	 8660F2F3 F4F5F4F5		abcdefab-cdef-23 32-11aa-45454545 4545	
Area length:	00000008			
Area value: D6C6C6E2 C5E3002C			OFFSET	
Area length:	00000006			
Area value: 05C8D6D5 C4C1			.HONDA	
Area length:	80000008			
Area value: D6C6C6E2 C5E30030		I	OFFSET	
Area length:	80000008			
Area value: C6C1C3C9 D3C9E3E8		1	FACILITY	
Area length:	80000008			
Area value: D6C6C6E2 C5E30034		1	OFFSET	
Area length:	00000006			
Area value: D7D9D6E3 E6D6		1	PROTWO	
Area length:	80000008			
Area value: D6C6C6E2 C5E30038		1	OFFSET	
Area length:	00000002			
Area value: 0006				
Area length:	80000008			

```
OFFSET..
  D6C6C6E2 C5E3003C
  Area length:
                                00000001
  Area value:
                                          Ι.
  04
  Area length:
                                000000A8
  Area value:
  C1C3C5C5 FF0000A8 02000000
                                00000000
                                            ACEE...y.....
  0000000
            07C9C2D4
                      E4E2C5D9
                                4004E2E8
                                            .....IBMUSER .SY
                                40404040
                                            S1 ~....
  E2F14040
            4040A110
                      0001054F
  40404040
            0000000
                      00000000
                                0000000
                                                 . . . . . . . . . . . .
  40404040
            40404040
                      00000000
                                00000000
  00000000
            00000000
                      40404040
                                40404040
  00000000
            006F67A8
                      0000000
                                0000000
                                            ....?.y.....
  0000000
                      0000000
                                0101054F
            006F67C0
                                             ....?.{......
  00000000
            00200000
                      00000000
                                00000000
                                            . . . . . . . . . . . . . . . .
                                            ....?.h
  00000000
            006F6888
  Area length:
                                00000050
  Area value:
  50010207
            0003C000
                      00000000
                                00000000
                                            &.....{......
  D7D6D2E5
            D4D4C3D3
                      C9C2D4E4
                                E2C5D940
                                            POKVMMCLIBMUSER
  D7D6D2E5
            D4D4C3D3
                                40404040
                                            POKVMMCLSYS1
                      E2E8E2F1
  C9D5E3D9
            C4D94040
                      00000000
                                00000000
                                            INTRDR .....
  C9C2D4E4
            E2C5D940
                      E2E8E2F1
                                40404040
                                            IBMUSER SYS1
  Area length:
                                00000090
  Area value:
                                00000000
  C1C3C5E7
            03000000
                      00FAB6F8
                                            ACEX.....8....
  00000000
            0000000
                      00000000
                                0000000
                                            00000000
            00000024
                      006F68D8
                                0000000
                                             ....?.Q....
  00000000
            00000000
                      00000000
                                0000000
  00000000
            00000000
                      00000000
                                00000000
  0000000
            00000000
                      00000000
                                0000000
  0000000
            00000000
                      00000000
                                0000000
  00000000
            00000000
                      00000000
                                0000000
  00000000
            00000000 00000000
                                00000000
  Hexadecimal dump of record follows:
+0000
      00000036 D9E3D9C1 C3C54040 D6D4E5E2
                                                 ....RTRACE OMVS
+0010
      D7D9C540
                00000000
                          00000000
                                    0000000
                                                PRE .....
+0020
                                    8B000BAE
      00000000
                00000000
                          00000000
                                                 . . . . . . . . . . . . . . . .
+0030
                                    00000000
      00000000
                0000000
                          0000000
                                                 . . . . . . . . . . . . . . . .
                                                .........?,...n.
+0040
      00000000
                00000000
                          006F6B00
                                    00FA9500
+0050
      00FA9500
                0000012E
                          0000012E
                                    D1F2F3C4
                                                 ..n.....J23D
+0060
      C3F0F0F2
                D1F2F3C4
                          C3F0F0F2
                                    006F6700
                                                C002J23DC002.?..
+0070
      006F6700
                00000000
                          B570BA31
                                    042B3327
                                                 .?.....
+0080
      00000000
                0000000
                          00000025
                                    00000025
                                                . . . . . . . . . . . . . . . .
+0090
      00000040
                0B001B2C
                          0B0016EC
                                    0B0016F0
                                                +00A0
      0B0016EC
                0B0016F4
                          0B0016EC
                                    0B0016F8
                                                 ......4......8
                                                 +00B0
      0B001700
                0B0016EC
                          0B0019A1
                                    0B0019C5
+00C0
      0B0019E9
                0B0019F2
                          0B001AE8
                                    0B001704
                                                ...Z...2...Y....
                80000008
                                                .....OFFSET...
+00D0
      0B001706
                          D6C6C6E2
                                    C5E30004
+00E0
      00000004
                00000000
                          80000008
                                    D6C6C6E2
                                                 .....OFFS
+00F0
      C5E30008
                00000004
                          00000000
                                    80000008
                                                ET.....
+0100
      D6C6C6E2
                C5E3000C
                          00000004
                                    0000000
                                                OFFSET.....
+0110
      80000008
                D6C6C6E2
                          C5E30010
                                    00000004
                                                 ....OFFSET.....
                                    C5E30014
+0120
      0000000
                80000008
                          D6C6C6E2
                                                .....OFFSET...
+0130
      00000004
                0000000
                          80000008
                                    D6C6C6E2
                                                 .....OFFS
+0140
                00000004
                          0000000
                                                ET......
      C5E30018
                                    00000008
```

Area value:

```
+0150
       D6C6C6E2
                 C5E3001C
                           00000004
                                     7FFF5268
                                                  OFFSET....."...
+0160
       8A000008
                 C1C3C5C5
                           FF0000A8
                                      02000000
                                                  ...yACEE...y....
+0170
       00000000
                 00000000
                           05C8D6D5
                                      C4C14040
                                                  .....HONDA
                                                   .SYS1 .....
                           40400101
+0180
       4004E2E8
                 E2F14040
                                      0001054F
+0190
       40404040
                 40404040
                           0000000
                                      0000000
                                                          . . . . . . . .
+01A0
       00000000
                 40404040
                           40404040
                                      0000000
+01B0
       00000000
                 00000000
                           00000000
                                      40404040
                                                     ....".&.....
+01C0
       40404040
                 0000000
                           7FFF5000
                                      0000000
                                                  00000000
                 0000000
                           7FFD3258
+01D0
                                      0000000
                                                  ...|......
+01E0
       0101054F
                 0000000
                           00A0000
                                      0000000
+01F0
       00000000
                 0000000
                           0000000
                                      7FFD3290
                                                  +0200
       00000000
                 00000000
                           7FFD3968
                                      00000050
+0210
       50010000
                 0000C000
                           00000000
                                      0000000
                                                  &.....{........
+0220
       00000000
                 0000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
                                                  . . . . . . . . . . . . . . . . . . .
+0230
       00000000
                 0000000
                           0000000
                                      0000000
+0240
       00000000
                 0000000
                           0000000
                                      0000000
+0250
       C8D6D5C4
                 C1404040
                           E2E8E2F1
                                      40404040
                                                  HONDA SYS1
+0260
       00000090
                 C1C3C5E7
                           03000000
                                      0000000
                                                  ....ACEX.....
+0270
       00000000
                 0000000
                           0000000
                                      0000000
                                                  +0280
       00000000
                 0000000
                           00000024
                                                  7FFD3000
+0290
       00000000
                 0000000
                           0000000
                                      0000000
+02A0
       00000000
                 00000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . .
                 0000000
+02B0
       00000000
                           00000000
                                      0000000
                                                  . . . . . . . . . . . . . . . .
+02C0
       00000000
                 0000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . .
+02D0
       00000000
                 00000000
                           0000000
                                      0000000
                 0000000
                           0000000
                                     00000000
+02E0
       00000000
                                                  .....OFFSET..
+02F0
       00000000
                 0000008
                           D6C6C6E2
                                      C5E30020
                                                  .....OFFS
+0300
       00000004
                 0000000
                           00000008
                                      D6C6C6E2
                 00000024
                           81828384
                                                  ET.....abcdefab
+0310
       C5E30024
                                      85868182
+0320
       60838485
                 86608182
                           838460F1
                                      F1818160
                                                  -cdef-abcd-11aa-
+0330
       F4F5F4F5
                 F4F5F4F5
                           F4F5F4F5
                                      00000008
                                                  4545454545....
       D6C6C6E2
+0340
                 C5E30028
                           00000024
                                      81828384
                                                  OFFSET.....abcd
                 60838485
                                                  efab-cdef-2332-1
+0350
       85868182
                           8660F2F3
                                      F3F260F1
+0360
       F1818160
                 F4F5F4F5
                           F4F5F4F5
                                      F4F5F4F5
                                                  1aa-454545454545
                                                  ....OFFSET.....
+0370
       80000008
                 D6C6C6E2
                           C5E3002C
                                      00000006
                                                  .HONDA....OFFSET
                 C4C10000
                           0008D6C6
                                      C6E2C5E3
+0380
       05C8D6D5
                                                  .....FACILITY..
+0390
       00300000
                 0008C6C1
                           C3C9D3C9
                                      E3E80000
+03A0
       0008D6C6
                 C6E2C5E3
                           00340000
                                      0006D7D9
                                                  ..OFFSET.....PR
+03B0
       D6E3E6D6
                 80000008
                           D6C6C6E2
                                      C5E30038
                                                  OTWO....OFFSET..
+03C0
       00000002
                 00060000
                           0008D6C6
                                      C6E2C5E3
                                                  ....OFFSET
                                                  ....yACEE.
+03D0
       003C0000
                 00010400
                           0000A8C1
                                      C3C5C5FF
                 0000000
+03E0
       0000A802
                           0000000
                                      00000007
                                                  ..y......
+03F0
       C9C2D4E4
                 E2C5D940
                           04E2E8E2
                                      F1404040
                                                  IBMUSER .SYS1
                           40404040
                                      40404000
                                                   ~....
+0400
       40A11000
                 01054F40
+0410
       00000000
                 00000000
                           00000040
                                      40404040
                                                  . . . . . . . . . . .
+0420
       40404000
                 0000000
                           0000000
                                      0000000
                                                    . . . . . . . . . . . . .
+0430
       00000040
                 40404040
                           40404000
                                      0000000
                                                  ...
+0440
       6F67A800
                 0000000
                           0000000
                                      0000000
                                                  ?.y.....
+0450
       6F67C000
                 00000001
                           01054F00
                                      0000000
                                                  ?.{.....
+0460
       20000000
                 0000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . .
                                                  ....?.8......
+0470
       00000000
                 6F67F800
                           0000000
                                      0000000
+0480
       6F688800
                 00005050
                           01020700
                                      03C00000
                                                  ?.h...&&.....{..
                                                  .....POKVMMCLI
+0490
       00000000
                 000000D7
                           D6D2E5D4
                                      D4C3D3C9
                                                  BMUSER POKVMMCLS
+04A0
       C2D4E4E2
                 C5D940D7
                           D6D2E5D4
                                      D4C3D3E2
+04B0
       E8E2F140
                 404040C9
                           D5E3D9C4
                                      D9404000
                                                  YS1 INTRDR .
+04C0
       0000000
                 000000C9
                           C2D4E4E2
                                      C5D940E2
                                                  .....IBMUSER S
+04D0
       E8E2F140
                 40404000
                           000090C1
                                      C3C5E703
                                                  YS1 ....ACEX.
                 FAB6F800
                                                  .....8......
+04E0
       00000000
                           00000000
                                      0000000
+04F0
       00000000
                 0000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . .
+0500
       00002400
                 6F68D800
                           00000000
                                      0000000
                                                  ....?.Q......
+0510
       00000000
                 0000000
                           0000000
                                      0000000
+0520
       00000000
                 00000000
                           00000000
                                      0000000
                           0000000
                                      0000000
+0530
       00000000
                 00000000
+0540
       00000000
                 00000000
                           00000000
                                      0000000
                                      00000000
+0550
       00000000
                 0000000
                           0000000
                                                  . . . . . . . . . . . . . . . . .
+0560
       00000000
                 00000000
                           000000
              GMT-02/23/2001 15:50:35.825866
                                               LOC-02/23/2001 11:50:35.825866
```

62

USR57 F44 ASCB 00FA9500 JOBN J23DC002

Trace Ide Record Ey Trace Typ	ecatcher:		00000036 RTRACE OMVSPOST		
Ending Se Calling a			00000000	8B000BAE	
Primary j	/Subsystem obname:	:	J23DC002	•••••	
Primary a Primary A Home jobn	CEEP: ame:		0000012E 00000000 J23DC002	006F6700	
Home asid Home ACEE	P:		0000012E 00000000	006F6700	
Task addr Task ACEE Time:	P:		00000000 00000000 B570BA31	006F6B00 00000000 24A9A94B	
Error cla Service n RACF Retu RACF Reas	umber: rn code:		00000025 00000000 00000000		
	ea address	:	00000000 00000025	00000000	
Area leng	th:		00000040		
0B0016F4	e: 0B0016EC 0B0016EC 0B0019A1	0B0016F0 0B0016F8 0B0019C5	0B0016EC 0B001700 0B0019E9	0 48 ~EZ	
0B0019F2	0B001AE8	0B001704	0B001706	2Y	
Area leng			80000008		
Area valu D6C6C6E2				OFFSET	
Area leng	th:		00000004		
Area valu 00000000	e:				
Area leng	th:		00000008		
Area valu D6C6C6E2	e: C5E30008			OFFSET	
Area leng	th:		00000004		
Area valu 00000000	e:			l	
Area leng	th:		00000008		
Area valu D6C6C6E2				OFFSET	l
	th:		00000004		

Area leng	th:		80000000		
Area valu D6C6C6E2	e: C5E30010			OFFSET	
Area leng	th:		00000004		
Area valu 00000000	e:			1	
Area leng	th:		80000008		
Area valu D6C6C6E2	c5E30014			OFFSET	
Area leng	th:		00000004		
Area valu 00000000	e:			1	
Area leng	th:		00000008		
Area valu D6C6C6E2	e: C5E30018			OFFSET	
Area leng	th:		00000004		
Area valu 00000000	e:			1	
Area leng	th:		00000008		
Area valu D6C6C6E2	e: C5E3001C			OFFSET	
Area leng	th:		00000004		
Area valu 7FFF5268	e:			"	
Area leng	th:		8A000000		
Area valu C1C3C5C5 00000000 E2F14040 40404040 00000000 00000000 00000000	FF0000A8 05C8D6D5 40400101 00000000 40404040 00000000 7FF5000 7FFD3258 00A00000 00000000 7FFD3968	02000000 C4C14040 0001054F 00000000 00000000 40404040 00000000 000000	00000000 4004E2E8 40404040 00000000 00000000 40404040 000000	ACEEy	
Area leng	th:		00000050		
Area valu 50010000 00000000 00000000 00000000 C8D6D5C4	0000C000 00000000 00000000 00000000 C1404040	00000000 00000000 00000000 00000000 E2E8E2F1	00000000 00000000 00000000 00000000 40404040	&{	
Area leng	th:		00000090		

Area valu C1C3C5E7 00000000 00000000 00000000 00000000 0000	03000000 00000000 00000024 00000000 00000000	00000000 00000000 7FFD3000 00000000 00000000 00000000 00000000	00000000 00000000 00000000 00000000 0000		ACEX	
Area leng	th:		00000008			
Area valu D6C6C6E2					OFFSET	
Area leng	th:		00000004			
Area valu	e:					
Area leng	th:		00000008			
Area valu D6C6C6E2				ı	OFFSET	1
Area leng	th:		00000024			
Area valu 81828384 838460F1 F4F5F4F5	e:	60838485 F4F5F4F5	86608182 F4F5F4F5		abcdefab-cdef-ab cd-11aa-45454545 4545	
				1	4545	1
Area leng			80000000			
Area valu D6C6C6E2					OFFSET	
Area leng	th:		00000024			
Area valu 81828384 F3F260F1 F4F5F4F5		60838485 F4F5F4F5	8660F2F3 F4F5F4F5		abcdefab-cdef-23 32-11aa-45454545 4545	
Area leng	th:		00000008			
Area valu D6C6C6E2					OFFSET	
Area leng	th:		00000006			
Area valu 05C8D6D5					. HONDA	
Area leng	th:		00000008			
Area valu D6C6C6E2					OFFSET	
Area leng	th:		80000000			
Area valu C6C1C3C9					FACILITY	
Area leng	th:		80000000			

	Area valu D6C6C6E2				ı	OFFSET	1
	Area leng	th:		00000006			
	Area valu	e:					
	D7D9D6E3	E6D6				PROTWO	
	Area leng	th:		80000008			
	Area valu D6C6C6E2				ı	OFFSET	I
	Area leng	th:		00000002			
	Δ						
	Area valu 0006	e:				••	1
	Area leng	th:		80000000			
	Area valu						
	D6C6C6E2	C5E3003C			ı	OFFSET	
	Area leng	th:		00000001			
	Area valu	e:					1
	04				ı	•	I
	Area leng	th:		8A000008			
	Area valu						
	C1C3C5C5 00000000	FF0000A8 07C9C2D4	02000000 E4E2C5D9	00000000 4004E2E8		ACEEy	
	E2F14040	4040A110	0001054F	40404040		\$1 ~	
	40404040	00000000	00000000	00000000			
	40404040	40404040	00000000	00000000		• • • • • • • • • • • • • • • • • • • •	
	00000000	00000000	40404040	40404040		•••••	
	00000000	006F67A8	00000000	00000000		?.y	
	00000000	006F67C0 00200000	00000000	0101054F 00000000		?{	
	00000000	00000000	006F67F8	00000000	-		
	00000000	006F6888	00010710	0000000		?.h	
	Area leng	th:		00000050			
	Area valu	e:					
	50010207	0003C000	00000000	00000000		& {	
	D7D6D2E5	D4D4C3D3	C9C2D4E4	E2C5D940		POKVMMCLIBMUSER	
	D7D6D2E5	D4D4C3D3	E2E8E2F1	40404040		POKVMMCLSYS1	
	C9D5E3D9 C9C2D4E4	C4D94040 E2C5D940	00000000 E2E8E2F1	00000000 40404040		INTRDR IBMUSER SYS1	
	Area leng			00000090	'	15.100211 0.101	'
	Area valu C1C3C5E7	e: 03000000	00FAB6F8	0000000	1	ACEX8	1
	00000000	00000000	00000000	00000000		AUEA	
	00000000	00000000	006F68D8	00000000		?.Q	
	00000000	00000000	00000000	00000000			
	00000000	00000000	00000000	00000000		• • • • • • • • • • • • • • • • • • • •	
	00000000	00000000	00000000	00000000		• • • • • • • • • • • • • • • • • • • •	
	00000000	00000000 00000000	00000000	00000000			
	00000000	00000000	00000000	00000000			
					•		-
+0(Hexadecim 900 00000		record fo 9C1 C3C54		5E	2 RTRACE	OMVS

					l ====
+0010	D7D6E2E3	00000000	00000000	00000000	POST
+0020	00000000	00000000	00000000	8B000BAE	
+0030	00000000	00000000	00000000	00000000	
+0040	00000000	00000000	006F6B00	00FA9500	?,n.
+0050	00FA9500	0000012E	0000012E	D1F2F3C4	nJ23D
+0060	C3F0F0F2	D1F2F3C4	C3F0F0F2	006F6700	C002J23DC002.?
+0070	006F6700	00000000	B570BA31	24A9A94B	.?zz.
+0080	00000000	00000000	00000025	00000025	1
+0090	00000040	0B001B2C	0B0016EC	0B0016F0	0
+00A0	0B0016EC	0B0016F4	0B0016EC	0B0016F8	48
+00B0	0B001700	0B0016EC	0B0019A1	0B0019C5	E
+00C0	0B0019E9	0B0019F2	0B001AE8	0B001704	Z2Y
+00D0	0B001706	80000000	D6C6C6E2	C5E30004	OFFSET
+00E0	00000004	00000000	80000008	D6C6C6E2	OFFS
+00F0	C5E30008	00000004	00000000	80000000	ET
+0100	D6C6C6E2	C5E3000C	00000004	00000000	OFFSET
+0110	00000008	D6C6C6E2	C5E30010	00000004	OFFSET
+0120	00000000	80000008	D6C6C6E2	C5E30014	OFFSET
+0130	00000004	00000000	80000008	D6C6C6E2	OFFS
+0140	C5E30018	00000004	00000000	80000008	ET
+0150	D6C6C6E2	C5E3001C	00000004	7FFF5268	OFFSET"
+0160	00000012		FF0000A8	02000000	VACEE
		C1C3C5C5			yACEEy
+0170	00000000	00000000	05C8D6D5	C4C14040	HONDA .
+0180	4004E2E8	E2F14040	40400101	0001054F	.SYS1
+0190	40404040	40404040	00000000	00000000	
+01A0	00000000	40404040	40404040	00000000	
+01B0	00000000	00000000	00000000	40404040	
+01C0	40404040	00000000	7FFF5000	00000000	
+01D0	00000000	00000000	7FFD3258	00000000	"
+01E0	0101054F	00000000	00A00000	00000000	
+01F0	00000000	00000000	00000000	7FFD3290	
+0200	00000000	00000000	7FFD3968	00000050	&
+0210	50010000	0000C000	00000000	00000000	8
+0220	00000000	00000000	00000000	00000000	
+0230	00000000	00000000	00000000	00000000	
+0240					1
	00000000	00000000	00000000	00000000	
+0250	C8D6D5C4	C1404040	E2E8E2F1	40404040	HONDA SYS1
+0260	00000090	C1C3C5E7	03000000	00000000	ACEX
+0270	00000000	00000000	00000000	00000000	
+0280	00000000	00000000	00000024	7FFD3000	II
+0290	00000000	00000000	00000000	00000000	
+02A0	00000000	00000000	00000000	00000000	
+02B0	00000000	00000000	00000000	00000000	
+02C0	00000000	00000000	00000000	00000000	
+02D0	00000000	00000000	00000000	00000000	
0220					
+02E0	00000000	00000000	00000000	00000000	
+02F0	00000000	80000008	D6C6C6E2	C5E30020	OFFSET
+0300	00000004	00000000	80000008	D6C6C6E2	OFFS
+0310	C5E30024	00000024	81828384	85868182	ETabcdefab
+0320	60838485	86608182	838460F1	F1818160	-cdef-abcd-11aa-
					i
+0330	F4F5F4F5	F4F5F4F5	F4F5F4F5	00000008	454545454545
+0340	D6C6C6E2	C5E30028	00000024	81828384	OFFSETabcd
+0350	85868182	60838485	8660F2F3	F3F260F1	efab-cdef-2332-1
+0360	F1818160	F4F5F4F5	F4F5F4F5	F4F5F4F5	1aa-454545454545
+0370	80000008	D6C6C6E2	C5E3002C	00000006	OFFSET
					!
+0380	05C8D6D5	C4C10000	0008D6C6	C6E2C5E3	.HONDAOFFSET
+0390	00300000	0008C6C1	C3C9D3C9	E3E80000	FACILITY
+03A0	0008D6C6	C6E2C5E3	00340000	0006D7D9	OFFSETPR
+03B0	D6E3E6D6	80000008	D6C6C6E2	C5E30038	OTWOOFFSET
+03C0	00000002	00060000	0008D6C6	C6E2C5E3	OFFSET
+03D0	003C0000	00010400	0000A8C1	C3C5C5FF	yACEE.
+03E0	0000A802	00000000	00000000	00000007	y
+03F0	C9C2D4E4	E2C5D940	04E2E8E2	F1404040	IBMUSER .SYS1
+0400	40A11000	01054F40	40404040	40404000	~
+0410	00000000	00000000	00000040	40404040	ı
+0420	40404000	00000000	00000000	00000000	
+0430	00000040	40404040	40404000	00000000	

```
+0440 6F67A800 00000000 00000000
                                 00000000
                                           ?.y.....
+0450 6F67C000 00000001 01054F00
                                 00000000
                                            ?.{.....
+0460 20000000 00000000 00000000 000000000
+0470 00000000 6F67F800 00000000 00000000
                                            ....?.8......
+0480 6F688800 00005050 01020700 03C00000
                                           ?.h...&&.....{..
+0490 00000000 000000D7 D6D2E5D4 D4C3D3C9
                                            .....POKVMMCLI
                                           BMUSER POKVMMCLS
+04A0 C2D4E4E2 C5D940D7 D6D2E5D4 D4C3D3E2
+04B0 E8E2F140 404040C9 D5E3D9C4 D9404000
                                           YS1 INTRDR .
+04C0 00000000 000000C9 C2D4E4E2 C5D940E2
                                            .....IBMUSER S
+04D0 E8E2F140 40404000 000090C1
                                 C3C5E703
                                           YS1 ....ACEX.
+04E0
      00000000 FAB6F800 00000000
                                 00000000
                                           .....8......
+04F0 00000000 00000000 00000000
                                 00000000
                                           +0500 00002400 6F68D800 00000000
                                 00000000
                                            ....?.Q......
+0510 00000000 00000000 00000000
                                 00000000
                                            . . . . . . . . . . . . . . . . . . .
+0520 00000000 00000000 00000000
                                 0000000
                                            . . . . . . . . . . . . . . . . .
+0530 00000000 00000000 00000000
                                 0000000
+0540 00000000 00000000 00000000
                                 00000000
+0560 00000000 00000000 000000
            GMT-02/23/2001 15:50:35.958984 LOC-02/23/2001 11:50:35.958984
```

RACROUTE REQUEST=VERIFY: This is an example of SAF trace output for RACROUTE REQUEST=VERIFY (service type 5) PRE andPOST entries. Note that the column offsets are not exact but the content has not been altered.

```
**** GTFTRACE DISPLAY OPTIONS IN EFFECT ****
USR=ALL
**** GTF DATA COLLECTION OPTIONS IN EFFECT: ****
USRP option
              **** GTF TRACING ENVIRONMENT ****
      Release: SP7.0.3 FMID: HBB7706 System name: RACFR13
     CPU Model: 4381 Version: FF Serial no. 111515
USR57 F44 ASCB 00FA9B00
                                   JOBN RACF
     Following is a formatted R TRACE record.
     This trace record was generated by IRRTRC00 with IDENT(R TRACE).
    Trace Identifier:
                                  00000036
    Record Eyecatcher:
                                  RTRACE
                                RACFPRE
    Trace Type:
    Ending Sequence:
                                  . . . . . . . .
    Calling address:
                                  00000000
                                            8B04A24E
    Requestor/Subsystem:
                                  RSSC06 9
                                            RACF
    Primary jobname:
                                  RACF
    Primary asid:
                                  0000001D
    Primary ACEEP:
                                  00000000 006FFDC0
    Home jobname:
                                  RACF
    Home asid:
                                  0000001D
    Home ACEEP:
                                  00000000 006FFDC0
    Task address:
                                  00000000
                                            006EC1A0
     Task ACEEP:
                                  00000000
                                            00000000
    Time:
                                  B5773AAD
                                            0E780C4B
    Error class:
                                  . . . . . . .
    Service number:
                                  00000005
    RACF Return code:
                                  00000000
    RACF Reason code:
                                  00000000
    Return area address:
                                  00000000
                                            00000001
    Parameter count:
                                  0000000A
    Area length:
                                  00000068
```

Area leng	th:		000000A	3	
Area value C1C3C5C5 00000000 E2F14040 40404040 00000000 00000000 00000000	FF0000A8 07C9C2D4 4040A110 00000000 40404040 00000000 006FD0E8 00200000 0006FD70	02000000 E4E2C5D9 4001059F 00000000 00000000 40404040 00000000 000000	00000000 4004E2E3 D9C1C3C0 0000000 0000000 4040404 0000000 0101059 00000000 00000000	3	EEy
Area leng	th:		00000050	9	
Area value 50012204 00000000 00000000 00000000 C9C2D4E4 Area lengt	08004000 00000000 00000000 00000000 E2C5D940	00000000 00000000 00000000 00000000 E2E8E2F1	0000000 0000000 0000000 0000000 4040404	0 0 0 IB	MUSER SYS1
			00000031	,	
Area value C1C3C5E7 00000000 00000000 00000000 00000000 0000	03000000 00000000 00000024 00000000 00000000	00000000 0000000 006FE008 0000000 0000000 0000000 0000000 000000	0000000 0000000 0000000 0000000 0000000		EX?\
Hexadecima -0000 000000 -0010 D7D9C3 -0020 000000 -0030 D9E2E2 -0040 D9C1C3 -0050 00FA99 -0060 404040 -0070 006FF1 -0080 000000 -0090 0000000 -0090 00000000000	540 000000 00000000000000000000000000000	9C1 C3C54 900 00000 900 00000 9F9 00000 9H0 006EC 9HD 00000 3C6 40404 900 B5773 901 00000 900 00000	.040 D9C .000 0000 .000 880 .000 0000 .1A0 00F .01A0 00F .01A0 006 .0AAD 0E7 .00A 0000	LC3C6 00000 4A24E 00000 4A9B00 LC3C6 FFDC0 30C4B 00000 00000 000000 000000 000000 000000	RTRACE RACF PRE

```
+01D0
        00000000
                  00000000
                            00000000 40404040
                                                  . . . . . . . . . . . . . . . . . . .
 +01E0
        40404040
                  00000000
                            00000000
                                      0000000
                                                      . . . . . . . . . . . . .
 +01F0
        00000000
                  00000000
                            00000000
                                      00000000
       0101059F
                  00000000
                            00200000
 +0200
                                      00000000
 +0210 00000000 00000000
                            0000000
                                      006CF8A0
                                                  .....88....8
 +0220 00000000 00000000
                            006CF850
                                      00000050
 +0230
        50010003
                  4002C000
                            00000000
                                      00000000
                                                  &.... {.......
 +0240 00000000 00000000
                            00000000
                                      00000000
                                                  . . . . . . . . . . . . . . . . . . .
 +0250
        00000000 00000000
                            0000000
                                      0000000
 +0260
        F0F14040
                  40404040
                            0000000
                                      0000000
                                                  01
 +0270
        5CC2E8D7
                  C1E2E25C
                            40404040
                                      40404040
                                                  *BYPASS*
 +0280
        00000090
                  C1C3C5E7
                            03000000
                                      00000000
                                                  ....ACEX.....
                                      00000000
 +0290
        00000000
                  00000000
                            00000000
 +02A0
        00000000
                  0000000
                            0000000
                                      0000000
                                                  00000000
 +02B0
                  00000000
                            0000000
                                      0000000
 +02C0
        0000000
                  0000000
                            0000000
                                      0000000
 +02D0
       00000000
                  00000000
                            00000000
                                      00000000
       00000000
 +02E0
                  00000000
                            0000000
                                      0000000
 +02F0
        00000000
                  0000000
                            00000000
                                      0000000
 +0300
        00000000
                  0000000
                            00000000
                                      00000000
                                                  +0310
       00000000
                  8A00000A8
                            C1C3C5C5
                                      FF0000A8
                                                  ....yACEE...y
 +0320 02000000 00000000
                            00000000
                                      07C9C2D4
                                                  .....IBM
 +0330 E4E2C5D9 4004E2E8
                            E2F14040
                                                  USER .SYS1 ~.
                                      4040A110
 +0340 4001059F D9C1C3C6
                            40404040
                                      00000000
                                                   ...RACF ....
 +0350 00000000 00000000
                            40404040
                                      40404040
                                                  . . . . . . . .
 +0360 00000000 00000000
                            00000000 00000000
 +0370
        40404040
                 40404040
                            0000000
                                      006FD0E8
                                                     ....?}Y
 +0380
        00000000
                  0000000
                            0000000
                                      006FDFC8
                                                  +0390
        00000000
                  0101059F
                            0000000
                                      00200000
                                                  . . . . . . . . . . . . . . . .
                                                   . . . . . . . . . . . . . . . . . . .
 +03A0
        00000000
                  00000000
                            00000000
                                      00000000
                                      006FFD70
 +03B0
        006FFB48
                  00000000
                            00000000
                                                   .?.........
 +03C0
       00000050
                  50012204
                            08004000
                                      00000000
                                                  ...&&.....
 +03D0 00000000 00000000
                            00000000
                                      00000000
                                                  . . . . . . . . . . . . . . . .
 +03E0 00000000
                 00000000
                            0000000
                                      0000000
 +03F0 00000000 00000000
                            00000000
                                      00000000
                                                  ....IBMUSER SYS1
 +0400
        00000000
                  C9C2D4E4
                            E2C5D940
                                      E2E8E2F1
 +0410
        40404040
                  00000090
                            C1C3C5E7
                                      03000000
                                                      ....ACEX....
 +0420
        00000000
                  00000000
                            00000000
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
 +0430
        00000000
                  00000000
                            00000000
                                      00000024
                                                   . . . . . . . . . . . . . . . .
       006FE008
                                                   .?\.....
 +0440
                 00000000
                            00000000
                                      00000000
 +0450
        0000000 00000000
                            00000000
                                      00000000
 +0460
        00000000 00000000
                            00000000
                                      00000000
 +0470
        00000000 00000000
                            00000000
                                      0000000
        00000000 00000000
                            00000000
                                      0000000
 +0480
 +0490
        00000000
                  00000000
                            00000000
                                      00000000
 +04A0
        00000000
                  00000000
                                                  . . . . . . . .
               GMT-02/28/2001 19:57:22.490298 LOC-02/28/2001 15:57:22.490298
USR57 F44 ASCB 00FA9B00
                                   JOBN RACF
```

Following is a formatted R TRACE record.

This trace record was generated by IRRTRC00 with IDENT(R TRACE).

Trace Identifier: Record Eyecatcher: Trace Type:	00000036 RTRACE RACFPOST	
Ending Sequence:		00044045
Calling address:	00000000	8B04A24E
Requestor/Subsystem:	RSSC06 9	RACF
Primary jobname:	RACF	
Primary asid:	0000001D	
Primary ACEEP:	00000000	006FFDC0
Home jobname:	RACF	
Home asid:	0000001D	
Home ACEEP:	00000000	006FFDC0
Task address:	00000000	006EC1A0
Task ACEEP:	00000000	00000000
Time:	B5773AAD	0E8C548B

Error cla Service n RACF Retu RACF Reas Return ar Parameter	umber: rn code: on code: ea address count:	:	00000005 00000000 00000000 00000000 000000	0B0891C4
Area valu		00680200	00055800	1 1
0B089158 00000000 00400000 00000000	0B089160 00000068 00000000 00000000	0B08916C 00000000 00000000 00000000	00000000 00000000 00000000 00000000	jjj%
00000000	00000000	00000000	00000000	
Area leng	th:		0000006C	
Area valu 6C0000A0 00000000 00000000 00000000 000000	e: 0000000 0000000 0000000 08089154 0000000 0000000	00000000 0000000 0000000 0000000 000000	0000000 0000000 0000000 0000000 0000000	%j
Area leng	th:		8A00000A8	
Area valu C1C3C5C5 00000000 E2F14040 40404040 0000000 0000000 0000000 000000	e: FF0000A8 07C9C2D4 4040A110 00000000 40404040 00000000 006FD0E8 00200000 00000000 0006FD70	02000000 E4E2C5D9 4001059F 00000000 40404040 00000000 00000000 000000	00000000 4004E2E8 D9C1C3C6 00000000 00000000 40404040 00000000 0101059F 00000000 00000000	ACEEy
Area leng	th:		00000050	
Area valu 50012204 00000000 00000000 00000000 C9C2D4E4	08004000 00000000 00000000 00000000 E2C5D940	00000000 00000000 00000000 00000000 E2E8E2F1	00000000 0000000 0000000 0000000 40404040	&IBMUSER SYS1
Area length:			00000090	
Area valu C1C3C5E7 00000000 00000000 00000000 00000000 0000	e: 0300000 0000000 0000024 0000000 0000000 0000000 0000000 000000	0000000 0000000 006FE008 0000000 0000000 0000000 0000000 000000	0000000 0000000 0000000 0000000 0000000	ACEX?\

```
Hexadecimal dump of record follows:
+0000
       00000036 D9E3D9C1 C3C54040
                                     D9C1C3C6
                                                 ....RTRACE RACF
+0010
       D7D6E2E3
                00000000
                          00000000
                                     00000000
                                                 POST.....
+0020 00000000 00000000
                          00000000
                                     8B04A24E
                                                 .....s+
+0030 D9E2E2C3 F0F640F9
                          00000000 00000000
                                                 RSSC06 9.....
+0040 D9C1C3C6 40404040
                           006EC1A0 00FA9B00
                                                 RACF .>A....
                                                 .....RACF
+0050 00FA9B00 0000001D
                          0000001D D9C1C3C6
                                                  RACF .?.{
+0060 40404040 D9C1C3C6 40404040 006FFDC0
+0070
      006FFDC0 00000000
                                    0E8C548B
                                                 .?.{.....
                           B5773AAD
+0080
       00000000
                0B0891C4
                           00000005
                                     0000005
                                                 .....jD.....
                           00000000
                                     00680200
+0090
       00000068
                 00000000
                                                 +00A0
       00055800
                0B089158
                           0B089160
                                     0B08916C
                                                 .....j...j-..j%
+00B0
      00000000
                00000000
                           00000068
                                     00000000
                                                 . . . . . . . . . . . . . . . .
+00C0
      00000000
                00400000
                           0000000
                                     0000000
                                                 +00D0 00000000
                00000000
                           0000000
                                     0000000
                                                 . . . . . . . . . . . . . . . . . . .
+00E0
      00000000
                00000000
                           0000000
                                     0000000
+00F0 00000000
                00000000
                           00000000
                                     0000006C
+0100
       6C0000A0
                00000000
                           0000000
                                     00000000
                                                 %.....
+0110
       00000000
                 0000000
                           00000000
                                     0000000
                                                 . . . . . . . . . . . . . . . .
       00000000
                 0000000
                           0000000
                                     00000000
+0120
                                                 . . . . . . . . . . . . . . . . . . .
+0130
      00000000
                0B089154
                           00000000
                                     00000000
                                                 .....j......
+0140
      00000000 00000000
                          00000000
                                    00000000
                                                 . . . . . . . . . . . . . . . .
+0150 00000000 00000000
                          00000000
                                    00000000
                                                 . . . . . . . . . . . . . . . . . . .
+0160 00000000 00000000
                          00000000
                                    000000A8
                                                 ACEE...y.....
+0170 C1C3C5C5 FF0000A8
                          02000000 00000000
+0180 00000000 07C9C2D4
                           E4E2C5D9
                                                 .....IBMUSER .SY
                                     4004E2E8
                                                 S1 ~...RACF
+0190 E2F14040 4040A110
                          4001059F
                                     D9C1C3C6
+01A0 40404040
                00000000
                           0000000
                                     0000000
                                                    . . . . . . . . . . . . .
+01B0
       40404040
                 40404040
                           0000000
                                     0000000
                                                        . . . . . . . .
+01C0
       00000000
                00000000
                           40404040
                                     40404040
      00000000
+01D0
                006FD0E8
                           00000000
                                     00000000
                                                 .....?}Y.....
+01E0 00000000 006FDFC8
                           00000000
                                    0101059F
                                                 .....?.H......
+01F0 00000000 00200000
                           00000000
                                     00000000
                                                 . . . . . . . . . . . . . . . . .
+0200 00000000 00000000
                           006FFB48
                                     00000000
                                                 ....?....?
+0210 00000000 006FFD70
                           00000050
                                     50012204
                                                 .....?......&&....
+0220
      08004000
                00000000
                           0000000
                                     0000000
                                                 +0230
       00000000
                 0000000
                           0000000
                                     0000000
                                                 +0240
       00000000
                00000000
                           00000000
                                     0000000
                                                 . . . . . . . . . . . . . . . . . . .
+0250
      00000000
                00000000
                           00000000
                                     C9C2D4E4
                                                 .....IBMU
                                                 SER SYS1 ....
+0260 E2C5D940 E2E8E2F1
                           40404040
                                     00000090
+0270 C1C3C5E7 03000000
                          00000000
                                    00000000
                                                 ACEX.....
+0280 00000000 00000000
                           00000000 00000000
                                                 . . . . . . . . . . . . . . . . . . .
+0290 00000000 00000024
                          006FE008 00000000
+02A0 00000000 00000000
                          00000000 00000000
      00000000 00000000
+02B0
                           00000000 00000000
                                                 . . . . . . . . . . . . . . . .
+02C0
       00000000
                 0000000
                           0000000
                                     0000000
                                                 . . . . . . . . . . . . . . . .
+02D0
       00000000
                 00000000
                           0000000
                                     00000000
                                                 . . . . . . . . . . . . . . . .
+02E0
       00000000
                 00000000
                           00000000
                                     00000000
                                                 . . . . . . . . . . . . . . . . . . .
+02F0
       GMT-02/28/2001 19:57:22.490583 LOC-02/28/2001 15:57:22.490583
```

MANAGER ALTER: This is an example of a MANAGER ALTER trace with PRE and POST entries. Note that the column offsets are not exact but the content has not been altered.

```
**** GTFTRACE DISPLAY OPTIONS IN EFFECT ****
USR=ALL

**** GTF DATA COLLECTION OPTIONS IN EFFECT: ****
USRP option

**** GTF TRACING ENVIRONMENT ****
Release: SP7.0.3 FMID: HBB7706 System name: RACFR13
CPU Model: 4381 Version: FF Serial no. 111515
```

```
is a formatted R\_TRACE record.
This trace record was generated by IRRTRC00 with IDENT(R\_TRACE).
                               00000036
Trace Identifier:
Record Eyecatcher:
                               RTRACE
Trace Type:
                               MNGRPRE
Ending Sequence:
                               . . . . . . . .
Calling address:
                               00000000
                                         8B000BAE
Requestor/Subsystem:
                               . . . . . . . .
Primary jobname:
                               IBMUSER
Primary asid:
                               00000019
Primary ACEEP:
                               00000000 006FF608
Home jobname:
                               IBMUSER
Home asid:
                               00000019
Home ACEEP:
                               00000000
                                         006FF608
Task address:
                               00000000
                                         006B8220
Task ACEEP:
                               00000000
                                         00000000
Time:
                               B57740CE
                                         B8ED7F45
Error class:
                               . . . . . . .
Service number:
                               00000000
RACF Return code:
                               0000000
RACF Reason code:
                               0000000
                               00000000
Return area address:
                                         00000000
Parameter count:
                               00000006
Area length:
                               00000050
Area value:
08004102 0015FFDA 001468F8
                               00000000
                                            . . . . . . . . . . . 8 . . . .
00000000 00000000
                    00000000
                               01000000
                                           . . . . . . . . . . . . . . . . . . .
20000000 00000000
                    40404040
                               40404040
00000000 00000000
                    00000000
                               0000000
00000000 00000000
                    00000000
                               00000000
                                            . . . . . . . . . . . . . . . .
Area length:
                               00000008
Area value:
D6C6C6E2 C5E30004
                                         OFFSET..
Area length:
                               00000004
Area value:
03D1D1D7
                                         JJP
Area length:
                               8A000000
Area value:
C1C3C5C5 FF0000A8 02000000
                               00000000
                                           ACEE...y.....
00000000 07C9C2D4
                    E4E2C5D9
                               4004E2E8
                                            .....IBMUSER .SY
                                           S1 ~....
E2F14040 4040A110 0001059F
                               40404040
40404040
          00B28CA0
                    00000000
                               00000000
                                                . . . . . . . . . . . .
D3D6C3C1 D3C3F1F0
                    00000000
                               0000000
                                           LOCALC10.....
00000000
          00000000
                    40404040
                               40404040
                    00000000
00000000 006FDF98
                               00000000
                                            .....?.q......
          006FD120
00000000
                    00000000
                               0101059F
                                            .....?J......
00000000 00200000
                    00000000
                               00000000
                                            . . . . . . . . . . . . . . . . . . .
00000000 00000000
                    006FF578 7F6F5000
                                           .....?5."?&.
                                           ....?..
00000000 006FDFB0
Area length:
                               00000050
Area value:
50010206 00010000 00000000 00000000 | &.....
```

```
00000000
             00000000
                       00000000
                                  0000000
                                              . . . . . . . . . . . . . . . .
  0000000
             00000000
                       00000000
                                  0000000
                                              . . . . . . . . . . . . . . . . . . .
  D3D6C3C1
             D3C3F1F0
                       00000000
                                  00000000
                                              LOCALC10.....
             E2C5D940
                                              IBMUSER SYS1
  C9C2D4E4
                       E2E8E2F1
                                  40404040
  Area length:
                                  00000090
  Area value:
             03000000
                       00000000
                                 00000000
  C1C3C5E7
                                              ACEX.....
  00000000
             0000000
                       00000000
                                  0000000
                                              0000000
             00000024
                       006FF868
                                  0000000
                                              ....?8.....
  00000000
             00000000
                       00000000
                                  00000000
                                              . . . . . . . . . . . . . . . .
  00000000
             00000000
                       00000000
                                  00000000
                                              . . . . . . . . . . . . . . . .
  0000000
             0000000
                       0000000
                                  0000000
   0000000
             00000000
                       00000000
                                  0000000
  0000000
             0000000
                       00000000
                                  0000000
  00000000
             00000000
                       00000000
                                 00000000
  Hexadecimal dump of record follows:
+0000
       00000036 D9E3D9C1 C3C54040
                                                  ....RTRACE MNGR
                                      D4D5C7D9
+0010
       D7D9C540
                 00000000
                           00000000
                                      0000000
                                                  PRE .....
+0020
       00000000 00000000
                           00000000
                                     00000000
                                                  . . . . . . . . . . . . . . . .
       00000000 00000000
                           00000000
+0030
                                     00000000
                                                  . . . . . . . . . . . . . . . . . . .
+0040
       00000000 00000000
                           006B8220
                                      00FACD00
                                                  ....,b....
+0050 00FACD00 00000019
                           00000019
                                      C9C2D4E4
                                                   .....IBMU
+0060 E2C5D940 C9C2D4E4
                           E2C5D940
                                                  SER IBMUSER .?6.
                                     006FF608
                 00000000
+0070
       006FF608
                           B57740CE
                                      B8ED7F45
                                                  +0080
       00000000
                 00000000
                           00000006
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
+0090
       00000050
                            0015FFDA
                                                  ....8
                 08004102
                                      001468F8
+00A0
       00000000
                 00000000
                           00000000
                                      00000000
                                                   . . . . . . . . . . . . . . . .
                 20000000
+00B0
       01000000
                           0000000
                                      40404040
                                                   . . . . . . . . . . . .
+00C0 40404040
                 00000000
                           00000000
                                      00000000
+00D0 00000000
                 00000000
                           00000000
                                      00000000
                                                  .....OFFSET...
+00E0 00000000
                 80000008
                           D6C6C6E2
                                      C5E30004
+00F0 00000004
                 03D1D1D7
                           8A000000
                                      C1C3C5C5
                                                   .....JJP....yACEE
+0100 FF0000A8
                 02000000
                           00000000
                                      00000000
                                                   ...y......
+0110
       07C9C2D4
                 E4E2C5D9
                           4004E2E8
                                      E2F14040
                                                  .IBMUSER .SYS1
+0120
       4040A110
                 0001059F
                            40404040
                                      40404040
                                                    ~....
+0130
       00B28CA0
                 00000000
                           00000000
                                      D3D6C3C1
                                                    ....LOCA
                                      00000000
+0140
      D3C3F1F0
                 00000000
                           00000000
                                                  LC10.....
+0150 00000000
                 40404040
                           40404040
                                      00000000
                                                  ....
+0160 006FDF98 00000000
                           0000000
                                      00000000
                                                  .?.q.....
+0170 006FD120 00000000
                           0101059F
                                      0000000
                                                  .?J.....
+0180 00200000 00000000
                           00000000
                                      00000000
                                                   .....?5."?&.....
+0190
       00000000
                 006FF578
                           7F6F5000
                                      00000000
+01A0
       006FDFB0
                 00000050
                           50010206
                                      0001C000
                                                  +01B0
       0000000
                 00000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
+01C0
       00000000
                 00000000
                           0000000
                                      0000000
                                                   . . . . . . . . . . . . . . . .
                                                   ....LOCALC10
+01D0
       00000000
                 00000000
                           D3D6C3C1
                                      D3C3F1F0
+01E0
      00000000
                 00000000
                           C9C2D4E4
                                      E2C5D940
                                                   .....IBMUSER
+01F0 E2E8E2F1
                 40404040
                           00000090
                                      C1C3C5E7
                                                  SYS1 ....ACEX
+0200
       03000000
                 0000000
                            0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
+0210
       00000000
                 00000000
                           00000000
                                      00000000
+0220
       00000024
                 006FF868
                           00000000
                                      0000000
                                                   .....?8......
+0230
       00000000
                 00000000
                            00000000
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
+0240
       00000000
                 00000000
                            00000000
                                      00000000
+0250
       00000000
                 00000000
                           0000000
                                      0000000
+0260
       00000000
                 00000000
                           00000000
                                      00000000
+0270
       00000000
                 0000000
                           0000000
                                      00000000
+0280
       00000000
                 00000000
                           00000000
              GMT-02/28/2001 20:24:48.404209 LOC-02/28/2001 16:24:48.404209
```

USR57 F44 ASCB 00FACD00 JOBN IBMUSER

is a formatted R_TRACE record. This trace record was generated by IRRTRC00 with IDENT(R_TRACE).

	Trace Ide Record Ey Trace Typ Ending Se Calling a Requestor Primary j Primary A Home jobn Home asid Home ACEE Task addr Task ACEE	ecatcher: e: quence: ddress: /Subsystem obname: sid: CEEP: ame: : P:	:	00000036 RTRACE MNGRPOST 00000000 IBMUSER 0000019 00000000 IBMUSER 00000019 00000000 00000000	8B000BAE
	Time: Error cla Service n RACF Retu RACF Reas Return ar Parameter	umber: rn code: on code: ea address	:	B57740CE 00000000 0000000 0000000 0000000	C6AEBD85
	Area leng			00000050	
	08004102 00000000 20000000 00000000 00000000		001468F8 00000000 C2C1E2C5 00000000 00000000	00000000 01000000 40404040 00000000 00000000	8 BASE
	Area leng	th:		80000008	
	Area valu D6C6C6E2				OFFSET
	Area leng	th:		00000004	
	Area valu 03D1D1D7	e:			.JJP
	Area leng	th:		8A00000A8	
	Area valu C1C3C5C5 00000000 E2F14040 40404040 D3D6C3C1 00000000 00000000 00000000 00000000 0000	e: FF0000A8 07C9C2D4 4040A110 00B28CA0 D3C3F1F0 00000000 006FDF98 006FD120 00200000 00000000 006FDFB0	02000000 E4E2C5D9 0001059F 0000000 0000000 40404040 0000000 000000	00000000 4004E2E8 40404040 00000000 00000000 40404040 000000	ACEEyIBMUSER .SY S1 ~ LOCALC10?.q?5."?&
Area length:				00000050	
	Area valu 50010206 00000000 00000000 D3D6C3C1 C9C2D4E4	e: 0001C000 00000000 00000000 D3C3F1F0 E2C5D940	00000000 00000000 00000000 00000000 E2E8E2F1	00000000 00000000 00000000 00000000 40404040	&{

```
Area length:
                                 00000090
   Area value:
  C1C3C5E7
             03000000
                       0000000
                                 0000000
                                              ACEX.....
  00000000
             00000000
                       00000000
                                 00000000
                                              . . . . . . . . . . . . . . . . . . .
  00000000
             00000024
                       006FF868
                                 0000000
                                              00000000
             00000000
                       00000000
                                 0000000
  0000000
             00000000
                       00000000
                                 0000000
  0000000
             00000000
                       00000000
                                 0000000
  0000000
             0000000
                       0000000
                                 0000000
  0000000
             00000000
                       0000000
                                 0000000
                                              . . . . . . . . . . . . . . . .
  00000000
             00000000
                       00000000
                                 00000000
  Hexadecimal dump of record follows:
       00000036 D9E3D9C1 C3C54040
+0000
                                     D4D5C7D9
                                                  ....RTRACE MNGR
+0010
       D7D6E2E3
                 0000000
                           0000000
                                      0000000
                                                  POST.....
                                      00000000
+0020
       00000000
                 00000000
                           00000000
       00000000
+0030
                 0000000
                           0000000
                                      0000000
+0040
       00000000
                 0000000
                           006B8220
                                      00FACD00
+0050
       00FACD00
                 00000019
                           00000019
                                      C9C2D4E4
                                                  .....IBMU
+0060
       E2C5D940
                 C9C2D4E4
                           E2C5D940
                                      006FF608
                                                  SER IBMUSER .?6.
      006FF608
+0070
                 00000000
                           B57740CE
                                     C6AEBD85
                                                  .?6..... .F..e
+0080
       00000000
                 00000000
                           0000006
                                      0000000
                                                  . . . . . . . . . . . . . . . .
       00000050
+0090
                 08004102
                           0015FFDA
                                      001468F8
                                                  ....8
+00A0
       00000000
                 00000000
                           00000000
                                     00000000
       01000000
                 20000000
                           0000000
+00B0
                                      C2C1E2C5
                                                  .....BASE
+00C0
       40404040
                 0000000
                           0000000
                                      0000000
                                                      . . . . . . . . . . . . .
+00D0
       00000000
                 0000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
+00E0
       00000000
                 80000008
                           D6C6C6E2
                                      C5E30004
                                                  .....OFFSET...
+00F0
       00000004
                 03D1D1D7
                           8A000000
                                      C1C3C5C5
                                                  .....JJP...yACEE
      FF0000A8
+0100
                 02000000
                           0000000
                                      00000000
                                                  ...y.......
                                                  .IBMUSER .SYS1
+0110
       07C9C2D4
                 E4E2C5D9
                           4004E2E8
                                      E2F14040
                                                    ~....
+0120
       4040A110
                 0001059F
                           40404040
                                      40404040
                                                  .....LOCA
+0130
       00B28CA0
                 0000000
                           0000000
                                      D3D6C3C1
+0140
                 00000000
                           0000000
       D3C3F1F0
                                      00000000
                                                  LC10.....
+0150
       0000000
                 40404040
                           40404040
                                      0000000
+0160
       006FDF98
                 00000000
                           0000000
                                      0000000
                                                  .?.q.....
+0170
       006FD120
                 00000000
                           0101059F
                                      0000000
                                                  .?J.....
+0180
       00200000
                 00000000
                           0000000
                                      00000000
                                                  .....?5."?&.....
+0190
       00000000
                 006FF578
                           7F6F5000
                                      00000000
+01A0
       006FDFB0
                 00000050
                           50010206
                                      0001C000
                                                  .?....&.....{.
       00000000
                 00000000
                           0000000
+01B0
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
+01C0
       00000000
                 00000000
                           00000000
                                     00000000
+01D0
       00000000
                 00000000
                           D3D6C3C1
                                     D3C3F1F0
                                                  ....LOCALC10
       00000000
                 00000000
+01E0
                           C9C2D4E4
                                      E2C5D940
                                                  ....IBMUSER
                                      C1C3C5E7
+01F0
       E2E8E2F1
                 40404040
                           00000090
                                                  SYS1 ....ACEX
+0200
       03000000
                 00000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . . . . .
+0210
       00000000
                 00000000
                           0000000
                                      0000000
                                                  . . . . . . . . . . . . . . . .
                                      00000000
+0220
       00000024
                 006FF868
                           00000000
                                                  .....?8.......
+0230
       00000000
                 0000000
                           0000000
                                      0000000
+0240
       00000000
                 00000000
                           0000000
                                      0000000
+0250
       0000000
                 0000000
                           0000000
                                      0000000
+0260
       00000000
                 00000000
                           00000000
                                      00000000
+0270
       00000000
                 00000000
                           0000000
                                      0000000
+0280
       0000000
                 0000000
                           0000000
                                                  . . . . . . . . . . . .
              GMT-02/28/2001 20:24:48.460550 LOC-02/28/2001 16:24:48.460550
```

Validating input

This explains how to validate input to RACF processes.

Identifying the caller of RACF

Prerequisites

- Obtaining a system dump
- Formatting a system dump

Introduction to procedure

When a RACF abend occurs, RACF might be the cause of the problem, or the program calling RACF might have passed an incorrect parameter list, which caused RACF to issue the abend. (The parameter list is the only input RACF gets from a caller.)

This describes how to determine what module issued the RACF macro.

Procedure

- 1. Look at the system dump and check the TCB with field TCBCMP (equal to the abend code).
- 2. Locate the RB that issued the RACF SVC (SVC 82, 83, 84, or 85). In this RB, get the address of the next sequential instruction from field RBOPSW. If no such RB exists, then the executing RACF service may be PC-entered. In this case, use the Alternative procedure.
- 3. Find this address in the system dump and scan backward for the eye-catcher (a module or CSECT name printed in readable form along the right margin of the dump). That is the name of the routine that issued the RACROUTE macro.

Note: If the address of the next sequential instruction after the RACROUTE macro is not in the system dump, check an LPA (link pack area) map to determine if it is within an LPA module. If it is within an LPA module, that module is the issuer of the RACROUTE macro.

- If the name you find is not the ICHRFR00 module, then the name found caused RACF to abend. (Note that the issuer of the RACF SVC may not have caused the original error but may have merely passed bad data created by yet another module that called it. The end of the bad data chain might be several callers away.)
- If the name you find is the ICHRFR00 module, then SAF (the security authorization facility) issued the RACF macro as requested by another module that issued the RACROUTE macro.

To determine who issued the RACROUTE macro, locate the "current task" in the system dump and check the active RBs.

- a. Find the PRB with a RACF SVC (SVC 82, 83, 84, or 85) in the RBRTPSW2 field.
- b. Find the next RB.
 - In a formatted dump that has been printed, this is the RB below the RB with the SVC.
 - On IPCS (interactive problem control system), this is the RB displayed below the RB with the SVC.
- · Check the general-purpose registers in this RB. Register 1 should have the same value as the trace entry for the SVC found in Step 3a. Register 13 points to the save area of the ICHRFR00 module.
- For RACROUTE functions other than VERIFY or VERIFYX:
 - Find the save area of the ICHRFR00 module and make sure that in the save area, the address at offset X'4' points to the save area of the ICHSFR00 module (the previous save area).

- For BACROUTE functions VERIFY or VERIFYX:
 - Find the save area of the ICHSFR00 module and make sure that in the save area, the address at offset X'4' points to the save area of the IRRSVY00 (or IRRSVX00) module (the previous save area).
 - Find the save area of the ICHRFR00 module and make sure that in the save area, the address at offset X'4' points to the save area of the ICHSFR00 module (the previous save area).
- Find the save area of the ICHRFR00 module and make sure that in the save area, the address at offset X'4' points to the save area of the ICHSFR00 module (the previous save area).
- Find the save area of the ICHSFR00 module and make sure that in the save area, the address at offset X'4' points to the save area of the issuer of the RACROUTE macro (the previous save area).
- Find the save area of the issuer of the RACROUTE macro. In the save area of the issuer of the RACROUTE macro, offset X'C' is the contents of Register 14 of the module that issued the RACROUTE macro. Register 14 contains the address of the instruction after the RACROUTE macro.
- · Find this address in the system dump and scan backward for the eye-catcher (a module or CSECT name printed in readable form along the right margin of the dump). That is the name of the routine that issued the RACROUTE macro.

Alternative procedure

- 1. Look at the system dump and issue the IPCS command, SUMMARY FORMAT, to format the linkage stack for the failing task or SRB. In most cases, the top entry on this linkage stack represents the current RACF service; this can be validated by taking the formatted PSW for the stack entry and scrolling backward in memory in search of a module eyecatcher that has a RACF prefix, ICH or IRR.
- 2. If this stack entry represents a RACF service, then general purpose register 13 should point to a standard save area, and the caller of RACF can be located by tracing backward through a chain of such areas. If these steps do not appear to have produced the caller of RACF, then you cannot determine the caller of RACF without additional support.

Checking the parameter list passed to RACF

Prerequisites


- Obtaining a system dump
- Formatting a system dump.

How to check the parameter list passed to RACF

This procedure is useful only for a RACF macro request that was active when the system dump was generated.

- 1. Find the save area for the routine that issued the RACF macro. This can be found either in the trace-table entry for the SVC associated with the RACF macro, or in the RBs in a formatted dump. See Identifying the caller of RACF.
- 2. In the save area, find the contents of register 1.
 - If register 1 is zero, then the RACROUTE macro was issued and module ICHRFR00 issued the RACF macro. In this case, register zero points to a two-word parameter list. The first word of this parameter list points to the RACF SVC parameter list, and the second word of this parameter list points

to the SAF parameter list. This is shown:



- If register 1 is not zero, then this is the address of the parameter list passed with the macro request.
- 3. Find the address in the storage portion of the system dump. The values in the dump are the actual parameter list as seen by the system when processing the RACF request.
- 4. Use the description of the parameter list from Parameter list descriptions to decode the actual parameter list.

Note: For some parameter lists (such as RACROUTE REQUEST=AUTH, RACROUTE REQUEST=DEFINE, and RACROUTE REQUEST=VERIFY) the length of the parameter list varies from release to release. Check the first byte of these parameter lists for the actual length used.

- 5. Use these checks to determine whether the active RACF macro request had an error. You can do the checks most efficiently if you have a listing of the program that issued the macro.
 - a. Did the RACF macro request that invoked RACF services use valid keyword values, including addresses?
 - b. Did the caller supply a register save area for the RACF macro?
 - c. Do the caller's storage areas contain correct values?

You could check the system dump for application program storage areas that appear to have incorrect values, such as missing printable identifiers for modules or control blocks. Key storage areas are pointed to by the register save area for the RACF macro. (Incorrect values are generally caused by logic problems due to incorrect addresses.)

This check is especially important for these types of unexpected abends, which might involve a logic error in either the application program that issued the RACF macro or a system routine:

- A X'0Cx' abend, such as X'0C4'
- A cancel (a X'x22' abend)

Alternative procedure to check the parameter list passed to

After you find the caller of RACF, the first word of the parameter list pointed to from the stack entry should contain the address of the parameters passed to RACF on the request.

Searching for a matching problem

Prerequisites

- 1. See Performing a preliminary search for a matching problem for a description of easily located problem symptoms to use to find a matching problem.
- 2. See Troubleshooting the problem for the diagnostic procedures to follow to collect additional symptoms needed for a search.

For problems involving system dumps, you need to follow the diagnostic procedures in Obtaining a system dump and Formatting a system dump

How to search for a matching problem

This procedure summarizes search symptoms that you can collect by using this document's problem analysis procedures for RACF. You might want to use these symptoms to search for a matching problem in a problem database, or to report to IBM.

If you need descriptions or examples of entire search arguments, see the prerequisite procedure, Performing a preliminary search for a matching problem.

Scan Table 19 for additional RACF symptoms that you might want to use in your search for a matching problem (or to report to IBM). It lists some of the most probable search symptoms for problems in RACF.

Note: For abends, additional symptoms such as a register/PSW (program status word) difference and a failing instruction area are automatically produced in DAEDATA output, so they are not repeated here. Notes[®] about the symptoms are indicated with asterisks (*) and *Note *n**, where *n* is the number of the note.

Table 19. Additional Search Symptoms for RACF

Description of Search Symptom	Free-Format Example	Structured Example	
Control block name	ACEE	FLDS/ACEE	
Control block field name *Note 1*	ACEEFLG1	FLDS/ACEEFLG1	
Symptoms for later searches			
Level of failing module *Note 2*	HRF2220 or UW09958	LVLS/HRF2220 or PTFS/UW09958	

Notes:

- If you receive too many matches on your first search, consider adding a control block field name or other text from a RACF error message. (Avoid use of addresses or other values that would vary between executions of the RACF function.)
- The ID and level at the beginning of a failing module might be pointed to by RACF's PSW at the time of the failure. For abends, the module level might be in the SDWAMLVL field and in DAEDATA output.

Application Identity Mapping Considerations

The conversion utility IRRIRA00 processes a RACF database to activate the function that controls the indexing of application identities for existing databases. IRRIRA00 is responsible for handling the non-RACF application identities that compose the alias index. The term 'alias' refers to any non-RACF application user identity (such as identities for products including Lotus Notes for z/OS, Novell Directory Services for OS/390, and z/OS UNIX System Services) that is part of this index structure.

For more information on the IRRIRA00 utility and the stages of application identity mapping, see *z/OS Security Server RACF System Programmer's Guide*.

Considerations

IRRIRA00 activates this in four stages controlled by the installation and lists the current stage of the active primary database. Down-level systems do not have any support for application identity mapping, so errors might occur if the RACF database is shared by systems running releases prior to Version 2 Release 10. Therefore, we strongly recommend you make your changes from your Version 2 Release 10 system only. To prevent changes being made from a down-level system inadvertently, do one of the following before running IRRIRA00:

- Migrate all your systems to Version 2 Release 10
- Use the command protection steps described in z/OS Security Server RACF Security Administrator's Guide

These examples point out problems that can occur when sharing the RACF database with a system running Version 2 Release 10 or higher that has the application identity mapping support at stage 1 or higher and a down-level system system:

- You ADD a user or group profile with an application identity on a down-level system. The IRRUT200 report will run successfully on the Version 2 Release 10 system, but will show that the mapping profiles were created though no alias indices were ever created.
- You ALTER an application identity field in a user or group profile with a different application identity on the down-level system. The IRRUT200 report will run successfully on the Version 2 Release 10 system, but will show that the new mapping profiles were created though the old alias indices still exists. You must also issue the LISTUSER or LISTGRP command or run DBUNLOAD and compare the output to the IRRUT200 output in order to see differences.
- You DELETE a user or group profile with a mapping on the down-level system. The IRRUT200 report will run successfully on the Version 2 Release 10 system, but will show the mapping profiles have been deleted though the old alias indices still exist.

Additionally, if base profiles containing application identities are incorrectly manipulated from a down-level system, the alias index will not be updated.

LOGREC data set entries for the alias index

In all stages the getUMAP, getGMAP, and R-usermap callable services will report unexpected ICHEINTY and RACROUTE return codes (non-zero return codes other than indicating the profile was not found) with a LOGREC entry. Additionally, if locating an alias index entry fails but a mapping profile is found for a database at Stage 2, the callable service will write an entry to the LOGREC data set with a return code of X'0000000C' and a reason code of X'00000000'. The presence of these LOGREC entries indicates that the alias index is not complete and must be corrected before moving to Stage 3. The variable data for services IRRRGM01 (GID to group name mapping service), IRRRUM01 (UID to user ID mapping service) and IRRRIM00 (application ID to RACF user ID mapping service) serves as the RACF group name or user ID and as the entry name specified on the locate request for the alias index entry.

Recovering from errors with Application Identity Mapping

Prior to stage 3, RACF maintains mapping profiles and functionality to ensure mapping compatibility with down-level systems that share a database with higher-level systems. This means the RACF database is susceptible to errors if a mapping profile is inadvertently deleted, or if the mapping profile is modified so that the alias index entry does not match the corresponding USER profile, as seen in the previous examples.

With application identity mapping enabled at stage 3, RACF uses an alias index rather than mapping profiles to associate users and groups with specific application identities from products such as Lotus Notes for z/OS, Novell Directory Services for OS/390, or z/OS UNIX System Services. Though unlikely, it is possible that an unexpected error could cause an association mismatch that you can identify by comparing IRRUT200 alias index output with profile information returned from LISTUSER or LISTGRP (or DBUNLOAD). This area suggests methods to correct such inconsistencies.

If the mapping profile exists, and if your database is at stage 3, no profiles in class UNIXMAP, NOTELINK, or NDSLINK should exist. If you find one, you can ignore it just as RACF does. Otherwise, you can delete it using RDELETE. For example: RDELETE UNIXMAP U1

If the mapping profile contains lowercase letters, you cannot specify them on the RDELETE command. You must use BLKUPD or RACROUTE to delete the profile.

If your database is at stage 1 or higher and you believe the profile to be incorrect, consider one of these:

- If the alias index entry is missing, and if your database is at stage 0, you should not expect to see any alias index.
- If your database is at stage 1 or higher and you do not find any alias index entry corresponding to a specified application identity, you can regenerate the entry by altering the user or group profile with the desired application identity. For example, you can issue:

```
ALTUSER YOURID OMVS(UID(1))
```

 If the mapping profile associated with a user does not exist but the alias index entry does exist (at stage 1 or 2), you can remove the entry by temporarily adding the referenced profile with the indicated application identity, and then deleting the profile. For example, you can issue:

```
ADDUSER YOURID OMVS(UID(1))
DELUSER YOURID
```

 If an alias index entry references the incorrect user or group, but the user or group profile references a correct application identity, correct this by altering the user or group with the incorrect application identity, and then altering the user or group putting back the correct application identity. Suppose the alias index entry for the Lotus Notes for z/OS SNAME, USER1, references MYID rather than the desired YOURID. For example, you can issue:

```
ALTUSER MYID LNOTES(SNAME(USER1))
ALTUSER YOURID LNOTES(SNAME(USER1))
```

Using SAF Trace to debug IBM HTTP server problems

SAF Trace may be used to debug IBM HTTP server problems related to an incorrect SAF keyring configuration. In this area we will cover the steps needed to provide the appropriate output to be analyzed. We will also provide sample data for you to compare your output to.

Before you begin

You need to determine if the IBM HTTP server is using SAF keyrings.

Verify these lines are in httpd.main.conf:

```
sslmode on 
sslport 443
```

keyfile mysslring SAF

If the those lines do not exist in httpd.main.conf, **stop**, this diagnostic procedure does not apply.

• If the operator console says:

```
00 ICH408I USER(WEBSERV ) GROUP(IMWEB
                                     ) NAME(###############)
      IRR.DIGTCERT.LISTRING CL(FACILITY)
      INSUFFICIENT ACCESS AUTHORITY
      ACCESS INTENT(READ ) ACCESS ALLOWED(NONE )
```

you must give WEBSERV READ access to IRR.DIGTCERT.LSTRING in the FACULTY class. WEBSERV is the ID assigned to the web server process.

Starting the trace

Perform these steps to use SAF Trace to debug IBM HTTP server problems related to an incorrect SAF keyring configuration.

Turn SAF Trace on for IRRSDL00:

@SET TRACE(CALLABLE(TYPE(41)) JOBNAME(*))

2. Turn on GTF:

start gtfracf.gtf,,,noprompt

The order of trace calls

SSL calls the r datalib (IRRSDL00) callable service. For an error free SSL connection, SAF Trace will contain a pre and post record for the r_datalib functions in this order listed:

DataGetFirst initial DataGetFirst call that fails due to bad length

of parameters

DataGetFirst the first DataGetFirst call succeeds

CheckStatus

DataGetNext call fails due to bad length of parameters

DataGetNext call succeeds

CheckStatus

call fails because there are no more certificates in **DataGetNext**

the key ring

DataAbortQuery the call ending the query

Examples of each of the post records

Note: This trace was generated by IRRTRC00 with IDENT(R_TACE).

DataGetFirst

Trace Identifier: 00000036 Record Eyecatcher: RTRACE Trace Type: OMVSPOST Ending Sequence:

Calling address: 00000000 A6168CFA Requestor/Subsystem:

Primary jobname: IMWEBSRV Primary asid: 00000022

00000000 009FFDC0 Primary ACEEP:

IMWEBSRV Home jobname:

```
Home asid:
                              00000022
Home ACEEP:
                              0000000
                                        009FFDC0
Task address:
                              00000000
                                        009F0898
Task ACEEP:
                                        0000000
                              00000000
Time:
                              B5F9F4C7
                                        804A5686
Error class:
Service number:
                              00000029
RACF Return code:
                              00000000
RACF Reason code:
                              0000000
Return area address:
                              0000000
                                        00000000
Parameter count:
                              00000029
Area length:
                              00000034
Area value:
2561D0C0 25615600
                    256155F4
                              25615604
                                           ./}{./.../.4./..
         25615608
                    256155FC
                              256154D1
                                          ./.8./.../.J
256155F8
2561560C
         256154D2
                   2561D4C0
                              25615610
                                          ./.../.K./M{./..
A5615790
                                          v/..
                              00000008
Area length:
Area value:
D6C6C6E2 C5E30004
                                         OFFSET..
                              00000004
Area length:
Area value:
0000000
                                         | ....
Area length:
                              80000008
Area value:
D6C6C6E2 C5E30008
                                         OFFSET..
Area length:
                              00000004
Area value:
0000000
                              00000008
Area length:
Area value:
D6C6C6E2 C5E3000C
                                         OFFSET..
                              00000004
Area length:
Area value:
00000000
                              80000008
Area length:
Area value:
D6C6C6E2 C5E30010
                                         OFFSET..
```

Note: Offset 10 is the return code, which in this case is 0.

```
00000004
Area length:
Area value:
0000000
Area length:
                              80000008
Area value:
D6C6C6E2 C5E30014
                                         OFFSET..
                              00000004
Area length:
Area value:
0000000
Area length:
                              80000008
Area value:
D6C6C6E2 C5E30018
                                        OFFSET..
```

Note: Offset 18 is the reason code, which in this case is 0.

```
Area length: 00000004
Area value: 00000000 | ....
Area length: 00000008
Area value: D6C6C6E2 C5E3001C | OFFSET..
```

Note: Offset 1C is the Function code, which in this case is 01.. 01 is DataGetFirst

Area length: Area value:	00000001		
01		.	
Area length:	80000008		-
Area value: D6C6C6E2 C5E30020		OFFSET	1
Area length:	0000004	1	'
Area value: 00000000		I	ı
Area length:	8000000	1	'
Area value:		LAFFEET	
D6C6C6E2 C5E30024 Area length:	00000001	OFFSET	ı
Area value:			
00 Area length:	00000008		
Area value:	0000000		
D6C6C6E2 C5E30028		OFFSET	

Note: Offset 28 is the ring name found in .conf file, which in this case is MYSSLRING.

	0000000A		
D5C7		.MYSSLRING	
	80000008		
		l neeset	ı
	00000004	011321	1
		1	
	00000000		
	00000000		
		OFFSET	
	D5C7	D5C7 00000008	D5C7 .MYSSLRING 00000008 OFFSET 00000004

Note: Begining with offset 30, the remaining offsets contain the function specific parameter list (FSPL).

Area length: Area value:		00000048	
256157D8 00000002 256494B8 00000000 00000000 00000009	00000000 257DF558 256157EC	000002A5 00000000 08899999	./.Qv .m'5 /irr
838599A3 81000000 00000038 2561D5B0	0000004F	257DF870	certa .'8. /N.
Area length: Area value:		80000008	
D6C6C6E2 C5E30000 Area length: Area value:		00000014	OFFSET
25C9A040 00000000 00000000	00000000	00000000	.I
Area length: Area value:		80000008	1
D6C6C6E2 C5E30010			OFFSET

Note: Offset 10 is the certificate.

Area leng	th:		000002A5	
Area valu	e:			
308202A1	3082020A	A0030201	02020100	.b.~.b
300D0609	2A864886	F70D0101	05050030	f.f7
4D310B30	09060355	04061302	55533118	(

```
....(...|(&
30160603
         55040A13
                    0F4D5920
                              434F4D50
                                          .+....+......
414E592C
          20494E43
                    31243022
                              06035504
                                          0B131B48
          554D414E
                    20524553
                              4F555243
                                          .....
45532043
          45525449
                    46494341
                              5445301E
                    30353030
                                          . . . . . . . . . . . . . . . . . . ! .
170D3031
         30363038
                              30305A17
0D323030
          36313030
                    34353935
                              395A304D
                                          ....!.(
310B3009
         06035504
                    06130255
                              53311830
         040A130F
                                          . . . . . . . . ( . . . | (& .
16060355
                    4D592043
                              4F4D5041
4E592C20
                                          +....+......
          494E4331
                    24302206
                              0355040B
131B4855
          4D414E20
                    5245534F
                              55524345
                                          ....(.+....|....
53204345
          52544946
                    49434154
                              4530819F
                                          ....a.
300D0609
         2A864886
                    F70D0101
                              01050003
                                          ....f.f7.....
818D0030
         81890281
                    8100B3E1
                                          a...ai.aa...L?.t
                              D36F32A3
1ED16837
          8EF47012
                    0F74E1F7
                              CA9BA924
                                          .J...4....7..z.
                                          .-a5.;.i..o..d1.
456081F5
          6A5EDD89
                    35CA9674
                              4984F141
E44AB5E0
          F1B0DC82
                    75216B53
                              6FE7AC57
                                          U¢.\1..b..,.?X..
                                          P.+....VXf~<...z
D73D4ECD
          16161537
                    E5E786A1
                              4C0A09A9
                   D40F1B55
                                          ..V...¬.M.....2.
1464E572
          35AD5F9C
                              45FDF230
                    6B3AD28A
B0228334
          E6ED2A0A
                              B4AA789D
                                          ..c.W...,.K....
54FD84F2
                    C767CCCC
                              26EE3ED4
                                          ..d2.`..G.....M
          1279B011
013BD21F
          AEBFB074
                    6AE50203
                              010001A3
                                          ..K.....t
81903081
         8D304B06
                   09551D0F
                                          a..a.....f8.
                              0186F842
                              74656420
                                          ....>../....
010D043E
         133C4765
                    6E657261
                                          .`..../`
62792074
          68652053
                    65637572
                              65576179
20536563
         75726974
                    79205365
                              72766572
                                          ..?..
20666F72
         204F532F
                    33393020
                              28524143
4629300E
         0603551D
                   0F0101FF
                              04040302
                                          . . . . . . . . . . . . . . . .
0006300F
          0603551D
                   130101FF
                              04053003
                                          . . . . . . . . . . . . . . . .
                              0414D79A
0101FF30
          1D060355
                    1D0E0416
                                          .w...o.W..'.XgM
44A60457
          328E9635
                    E655137D
                              52E787D4
46D2300D
         06092A86
                                          .K....f.f7....
                    4886F70D
                              01010505
00038181
         0052EECE
                    337B3893
                              19B9D56B
                                          ..aa....#.1..N,
                                          ....I@(VA .T...W
AD725205
          C97C4DE5
                    C16D13E3
                              1EEA02E6
D00A29B1
          CA6490CC
                    0ABAD5B9
                              6C61F417
                                          }.....N.%/4.
                                          nS.N.Y...#K.T...
95E207D5
          CBE8B84B
                    1A7BD22A
                              E3BC0154
          8A4BB3DA
                    0D75D127
                                          .W....J..p.5
FDE66400
                              079743F5
00ED5E58
          DC4B1FF9
                    2937C930
                              E306B662
                                          ..;....9..I.T...
0096DD5C
          BE80A812
                    5F859566
                              15D86B0C
                                          .o.*..y.¬en..Q,.
ECF12799
          A58E813B
                    94FDF51E
                              45D9C3E2
                                          .1.rv.a.m.5..RCS
27C64C2E
                                          .F<..
         BD
Area length:
                              80000008
Area value:
D6C6C6E2 C5E30018
                                        OFFSET..
```

Note: Offset 18 is the private_key_ptr. In this case, the length of 0 indicates that there is no key.

Area length:	0000000
Area value:	0000000
Area length: Area value:	0000008
D6C6C6E2 C5E30028	OFFSET
DUCUCULZ CJLJUUZO	011361

Note: Offset 28 is the label.

Area length:		00000009		
Area value: D4E840D7 D2C940C3	C1		MY PKI CA	I
Area length:		80000008		
Area value:			1 0==0==	
D6C6C6E2 C5E3003C			OFFSET	
Area length:		0000004F		
Area value:				
304D310B 30090603	55040613	02555331	.(
18301606 0355040A	130F4D59	20434F4D	()	

50414E59 2C2049 040B131B 48554E 43455320 434552 Area length: Area value:	041 4E205245	22060355 534F5552 415445 00000008	8.++					
D6C6C6E2 C5E300 Area length:)44	00000038	OFFSET					
e: Offset 44 is the Subjects_DN.								

Area ren	yın:		00000036	
Note: Offset	44 is the S	Subjects_D	N.	
Area val	ue:			
F0F04BD6 E4D9C3C5 C54BD67E C9D5C34B	E47EC8E4 E24AC3C5 D4E84AC3 C37EE4E2	D4C1D54A D9E3C9C6 D6D4D7C1	D9C5E2D6 C9C3C1E3 D5E86B4A	00.0U=HUMAN¢RESO URCES¢CERTIFICAT E.O=MY¢COMPANY,¢ INC.C=US
Area len	gth:		8A000000	INC.C-03
Area val C1C3C5C5 00000000 E6C5C240 C2E2D9E5 40404040 00000000 00000000 00000000 000000	FF0000A8 07E6C5C2 40400101 00000000 40404040 00000000 009FDF90 009FFAE0 00200000 009FFD70	02000000 E2C5D9E5 0501163F 00000000 00000000 40404040 00000000 000000	00000000 4005C9D4 C9D4E6C5 00000000 00000000 40404040 009FFA78 0101163F 00000000 00000000	ACEEyWEBSERV .IM WEBIMWE BSRV
Area len	gth:		00000050	
Area val 50012004 00000000 00000000 00000000 E6C5C2E2 Area len	0000C000 00000000 00000000 00000000 C5D9E540	00000000 00000000 00000000 00000000 C9D4E6C5	00000000 00000000 00000000 00000000 C2404040 00000090	&{
Area val C1C3C5E7 00000000 00000000 00000000 00000000 0000	03000000 00000000 000000024 00000000 00000000	00000000 00000000 009FE008 00000000 7F877040 00000000 00000000 00000000 00000000	00000000 00000000 00000000 00000000 0000	ACEX
Area len	gth:		00000000	
Area value Hexadecii +0000 00000 00000 00000 00000 00000 00000	mal dump of 0036 D9E3E 00000 00000 00000 00000 00000 00000 0000	901 C3C54 000 00000 0000 00000 0000 00000 0000 009F0 0000 009F5 665 C2E2D 0000 009FF 1000 00000 1000 00000 1029 00000 15F4 25615 15FC 25615	040 D6D4E5 000 000000 000 000000 000 404000 000 000000 898 000000 C80 000000 9E5 C9D4E6 DC0 000000 000 B5F9F4 000 000000 034 2561D0 604 256155 4D1 256156	POST POST

+0100	00000000	80000008	D6C6C6E2	C5E30008	OFFSET
+0110	00000004	00000000	80000000	D6C6C6E2	0FFS
+0120	C5E3000C	00000004	00000000	00000008	ET
+0130	D6C6C6E2	C5E30010	00000000	00000000	
					OFFSET
+0140	80000008	D6C6C6E2	C5E30014	00000004	OFFSET
+0150	00000000	80000008	D6C6C6E2	C5E30018	OFFSET
+0160	00000004	00000000	80000008	D6C6C6E2	OFFS
+0170	C5E3001C	00000001	01000000	08D6C6C6	ETOFF
+0180	E2C5E300	20000000	04000000	00000000	SET
+0190	08D6C6C6	E2C5E300	24000000	01000000	.OFFSET
+01A0	0008D6C6	C6E2C5E3	00280000	000A09D4	
					OFFSETM
+01B0	E8E2E2D3	D9C9D5C7	80000008	D6C6C6E2	YSSLRINGOFFS
+01C0	C5E3002C	00000004	00000000	80000008	ET
+01D0	D6C6C6E2	C5E30030	00000048	256157D8	OFFSET/.Q
+01E0	00000002	00000000	000002A5	256494B8	vm.
+01F0	00000000	257DF558	00000000	00000000	'5
+0200	00000009	256157EC	08899999	838599A3	/irrcert
+0210	81000000	0000004F	257DF870	00000038	a .'8
+0220	2561D5B0	80000000	D6C6C6E2	C5E30000	./NOFFSET
+0230	00000014	25C9A040	00000000	00000000	I
+0240	00000000	00000000	80000008	D6C6C6E2	OFFS
+0250	C5E30010	000002A5	308202A1	3082020A	ETv.b.~.b
+0260	A0030201	02020100	300D0609	2A864886	f.f
+0270	F70D0101	05050030	4D310B30	09060355	7
+0280	04061302	55533118	30160603	55040A13	
+0290	0F4D5920	434F4D50	414E592C	20494E43	.((&.++.
+02A0	31243022	06035504	0B131B48	554D414E	(.+
+02B0	20524553	4F555243	45532043	45525449	
+02C0	46494341	5445301E	170D3031	30363038	
+02D0	30353030	30305A17	0D323030	36313030	!
+02E0	34353935	395A304D	310B3009	06035504	!.(
+02F0	06130255	53311830	16060355	040A130F	
+0300	4D592043	4F4D5041	4E592C20	494E4331	((&.++
					((α.ττ
+0310	24302206	0355040B	131B4855	4D414E20	(.+.
+0320	5245534F	55524345	53204345	52544946	
+0330	49434154	4530819F	300D0609	2A864886	f.f
+0340	F70D0101	01050003	818D0030	81890281	7aai.a
+0350	8100B3E1	D36F32A3	1ED16837	8EF47012	aL?.t.J4
+0360	0F74E1F7	CA9BA924	456081F5	6A5EDD89	7za5.;.i
+0370	35CA9674	4984F141	E44AB5E0	F1B0DC82	od1.U¢.\1b
+0380	75216B53	6FE7AC57	D73D4ECD	16161537	,.?XP.+
+0390	E5E786A1		1464E572	35AD5F9C	VXf~ <zv¬.< td=""></zv¬.<>
		4C0A09A9			!
+03A0	D40F1B55	45FDF230	B0228334	E6ED2A0A	M2c.W
+03B0	6B3AD28A	B4AA789D	54FD84F2	1279B011	,.Kd2.`
+03C0	C767CCCC	26EE3ED4	013BD21F	AEBFB074	GMK
+03D0	6AE50203	010001A3	81903081	8D304B06	.Vtaa
+03E0	09551D0F	0186F842	010D043E	133C4765	f8
+03F0	6E657261	74656420	62792074	68652053	>/`
+0400	65637572	65576179	20536563	75726974	/`
+0410	79205365	72766572	20666F72	204F532F	`?
+0420	33393020	28524143	4629300E	0603551D	
+0430	0F0101FF	04040302	0006300F	0603551D	
+0440	130101FF	04053003	0101FF30	1D060355	
+0450	1D0E0416	0414D79A	44A60457	328E9635	Pwo.
+0460	E655137D	52E787D4	46D2300D	06092A86	W'.XgM.Kf
+0470	4886F70D	01010505	00038181	0052EECE	.f7aa
+0480	337B3893	19B9D56B	AD725205	C97C4DE5	.#.1N,I@(V
+0490	C16D13E3	1EEA02E6	D00A29B1	CA6490CC	A .TW}
			95E207D5		N.%/4.nS.N.Y
+04A0	0ABAD5B9	6C61F417		CBE8B84B	
+04B0	1A7BD22A	E3BC0154	FDE66400	8A4BB3DA	.#K.TW
+04C0	0D75D127	079743F5	00ED5E58	DC4B1FF9	Jp.5;9
+04D0	2937C930	E306B662	0096DD5C	BE80A812	I.To.*y.
+04E0	5F859566	15D86B0C	ECF12799	A58E813B	¬enQ,1.rv.a.
+04F0	94FDF51E	45D9C3E2	27C64C2E	BD000000	m.5RCS.F<
+0500	08D6C6C6	E2C5E300	18000000	00000000	.OFFSET
+0510	08D6C6C6	E2C5E300	28000000	09D4E840	.OFFSETMY
+0520	D7D2C940	C3C10000	0008D6C6	C6E2C5E3	PKI CAOFFSET
10320	0/026940	62610000	00000000	COLZUDES	I LKT CH OLLDEI

+0530	003C0000	004F304D	310B3009	06035504	.(
+0540	06130255	53311830	16060355	040A130F	
+0550	4D592043	4F4D5041	4E592C20	494E4331	((&.++
+0560	24302206	0355040B	131B4855	4D414E20	(.+.
+0570	5245534F	55524345	53204345	52544946	
+0580	49434154	45000000	08D6C6C6	E2C5E300	OFFSET.
+0590	44000000	38F0F04B	D6E47EC8	E4D4C1D5	00.OU=HUMAN
+05A0	4AD9C5E2	D6E4D9C3	C5E24AC3	C5D9E3C9	¢RESOURCES¢CERTI
+05B0	C6C9C3C1	E3C54BD6	7ED4E84A	C3D6D4D7	FICATE.O=MY¢COMP
+05C0	C1D5E86B	4AC9D5C3	4BC37EE4	E2000000	ANY,¢INC.C=US
+05D0	A8C1C3C5	C5FF0000	A8020000	00000000	yACEEy
+05E0	00000000	0007E6C5	C2E2C5D9	E54005C9	WEBSERV .I
+05F0	D4E6C5C2	40404001	01050116	3FC9D4E6	MWEBIMW
+0600	C5C2E2D9	E5000000	00000000	00000000	EBSRV
+0610	00404040	40404040	40000000	00000000	
+0620	0000000	0000000	00404040	40404040	
+0630	40000000	00009FDF	90000000	00009FFA	
+0640	78000000	00009FFA	E0000000	00010116	
+0650	3F000000	00002000	00000000	00000000	
+0660	00000000	00000000	00009FFB	48000000	
+0670	00000000	00009FFD	70000000	50500120	
+0680	040000C0	0000000	0000000	00000000	{
+0690	0000000	0000000	0000000	00000000	
+06A0	00000000	00000000	00000000	00000000	
+06B0	0000000	0000000	0000000	00E6C5C2	WEB
+06C0	E2C5D9E5	40C9D4E6	C5C24040	40000000	SERV IMWEB
+06D0	90C1C3C5	E7030000	00000000	00000000	.ACEX
+06E0	00000000	00000000	00000000	00000000	
+06F0	00000000	00000000	24009FE0	08000000	
+0700	00000000	00000000	00000000	00000000	
+0710	00000000	00000000	007F8770	40000000	"g
+0720	00000000	00000000	00000000	00000000	
+0730	00000000	00000000	00000000	00000000	
+0740	00000000	00000000	00000000	00000000	
+0750	00000000	00000000	00000000	00000000	
+0760	00000000	00			l

Note: All remaining examples will only contain the Function Specific Parameter List (FSPL) part of the trace record. All functions have the same parameter in the r_datalib parameter list, with different values.

CheckStatus

D6C6C6E2 C5E30030 Area length:	OFFSET 00000008	- 1
Area value: 000002A5 256494B8 Area length:	vm.	I
Area value: D6C6C6E2 C5E30004	OFFSET	1

Note: Offset 4 is the Certificate.

Area leng	th:		000002A5		
Area valu	e:				
308202A1	3082020A	A0030201	02020100	.b.~.b	
300D0609	2A864886	F70D0101	05050030	f.f7	
4D310B30	09060355	04061302	55533118	(
30160603	55040A13	0F4D5920	434F4D50	((&	
414E592C	20494E43	31243022	06035504	.++	
0B131B48	554D414E	20524553	4F555243	(.+	
45532043	45525449	46494341	5445301E		
170D3031	30363038	30353030	30305A17	!.	
0D323030	36313030	34353935	395A304D	!.(
310B3009	06035504	06130255	53311830		
16060355	040A130F	4D592043	4F4D5041	((&.	

```
+....+.....
   4E592C20
             494E4331
                        24302206
                                  0355040B
                                               ....(.+....|....
   131B4855
             4D414E20
                        5245534F
                                  55524345
   53204345
             52544946
                        49434154
                                  4530819F
                                               ....a.
             2A864886
                       F70D0101
                                               .....f.f7.....
   300D0609
                                  01050003
   818D0030
                                               a...ai.aa...L?.t
             81890281
                       8100B3E1
                                  D36F32A3
   1ED16837
             8EF47012
                        0F74E1F7
                                  CA9BA924
                                               .J...4.....7..z.
   456081F5
             6A5EDD89
                        35CA9674
                                  4984F141
                                               .-a5.;.i..o..d1.
   E44AB5E0
             F1B0DC82
                       75216B53
                                               U¢.\1..b..,.?X..
                                  6FE7AC57
                        E5E786A1
   D73D4ECD
                                               P.+....VXf~<...z
             16161537
                                  4C0A09A9
   1464E572
             35AD5F9C
                        D40F1B55
                                  45FDF230
                                               ..V...¬.M....2.
   B0228334
             E6ED2A0A
                        6B3AD28A
                                  B4AA789D
                                               ..c.W...,.K....
   54FD84F2
             1279B011
                        C767CCCC
                                  26EE3ED4
                                               ..d2.`..G.....M
                                               ..K.....V.....t
   013BD21F
             AEBFB074
                        6AE50203
                                  010001A3
   81903081
             8D304B06
                        09551D0F
                                               a..a.....f8.
                                  0186F842
                                               ....>../....
   010D043E
             133C4765
                        6E657261
                                  74656420
   62792074
             68652053
                        65637572
                                  65576179
                                               .`..../`
             75726974
                        79205365
   20536563
                                  72766572
   20666F72
                        33393020
                                               ..?..
             204F532F
                                  28524143
   4629300E
             0603551D
                        0F0101FF
                                  04040302
                                               . . . . . . . . . . . . . . . . . . .
   0006300F
                        130101FF
                                  04053003
             0603551D
   0101FF30
             1D060355
                        1D0E0416
                                  0414D79A
                                               .....P.
                                               .w...o.W..'.XgM
   44A60457
                       E655137D
             328E9635
                                  52E787D4
   46D2300D
             06092A86
                                  01010505
                                               .K....f.f7.....
                        4886F70D
   00038181
             0052EECE
                       337B3893
                                  19B9D56B
                                               ..aa....#.1..N,
                                               ....I@(VA .T...W
   AD725205
             C97C4DE5
                       C16D13E3
                                  1EEA02E6
             CA6490CC
   D00A29B1
                       0ABAD5B9
                                  6C61F417
                                               }.....N.%/4.
   95E207D5
             CBE8B84B
                        1A7BD22A
                                  E3BC0154
                                               nS.N.Y...#K.T...
   FDE66400
             8A4BB3DA
                        0D75D127
                                  079743F5
                                               .W....J..p.5
                                               ..;....9..I.T...
   00ED5E58
             DC4B1FF9
                        2937C930
                                  E306B662
   0096DD5C
             BE80A812
                        5F859566
                                  15D86B0C
                                               .o.*..y.¬en..Q,.
   ECF12799
                        94FDF51E
                                               .1.rv.a.m.5..RCS
             A58E813B
                                  45D9C3E2
   27C64C2E BD
                                               .F<..
                                  8A000008
   Area length:
   Area value:
   C1C3C5C5 FF0000A8 02000000
                                  00000000
                                               ACEE...y.....
                                               .....WEBSERV .IM
                                  4005C9D4
   00000000
             07E6C5C2
                       E2C5D9E5
   E6C5C240
             40400101
                        0501163F
                                  C9D4E6C5
                                               WEB .....IMWE
   C2E2D9E5
             00000000
                        00000000
                                  00000000
                                               BSRV.....
   40404040
             40404040
                        00000000
                                  00000000
   00000000
             00000000
                        40404040
                                  40404040
   00000000
             009FDF90
                        00000000
                                  009FFA78
                                               . . . . . . . . . . . . . . . .
   00000000
             009FFAE0
                        00000000
                                  0101163F
                                               00000000
             00200000
                        00000000
                                  00000000
   00000000
             00000000
                        009FFB48
                                  00000000
                                               . . . . . . . . . . . . . . . .
   00000000
             009FFD70
                                               . . . . . . . .
   Area length:
                                  00000050
   Area value:
   50012004
             0000C000
                        00000000
                                  00000000
                                               &....{......
   00000000
             00000000
                        00000000
                                  00000000
                                                . . . . . . . . . . . . . . .
   00000000
             00000000
                        00000000
                                  00000000
                                               . . . . . . . . . . . . . . . . . . .
   00000000
             00000000
                        0000000
                                  00000000
                                               . . . . . . . . . . . . . . . .
   E6C5C2E2
             C5D9E540
                        C9D4E6C5
                                  C2404040
                                               WEBSERV IMWEB
   Area length:
                                  00000090
   Area value:
   C1C3C5E7
             03000000
                        00000000
                                  0000000
                                               ACEX.....
   00000000
             00000000
                        00000000
                                  0000000
                                               . . . . . . . . . . . . . . . .
   00000000
             00000024
                        009FE008
                                  00000000
                                               00000000
                        00000000
                                               . . . . . . . . . . . . . . . .
             00000000
                                  00000000
   00000000
             0000000
                        7F877040
                                  00000000
                                               ....."g. ....
   00000000
             00000000
                        00000000
                                  00000000
                                               . . . . . . . . . . . . . . . .
   00000000
             00000000
                        00000000
                                  0000000
                                               . . . . . . . . . . . . . . . . . . .
   00000000
             00000000
                        00000000
                                  00000000
                                               . . . . . . . . . . . . . . . . . . .
   00000000
             00000000
                       00000000
                                  00000000
   Area length:
                                  0000000
   Area value:
   Hexadecimal dump of record follows:
+0000 00000036 D9E3D9C1 C3C54040 D6D4E5E2 | ....RTRACE OMVS |
```

Heart Hear						
	+0010	D7D6E2E3	00000000	00000000	00000000	POST
+0030			00000000	00000000	00000000	
+0060						
Hornor H						
Horse						
+0090 009FFDCO 00000000 00000000						
+0080 0000001F 00000029 000000004 2561D000 .F*.						B2KV
Health						
+0000 25615600 256155FC 25615400 25615608 256155FC 25615400 25615608 -////.8 +0000 25615402 25615402 25615608 25615402 25615608 .//// +0100 0000000 0000000 0000000 0000000 0000000 0000000 0000000 00000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 0000000 000						
HORDO 25615608 25615604 25615610 25615605 25615402 25615402 25615402 25615610 25615540 25615402 25615402 25615610 25615540 25615402 25615400 25615540 25615610 25615600 25610000 256000000 25666662 25630000 25630000 25666662 25630010 25630000 25666662 25630010 25630010 256300000 25630000						
+006E0 25615402 25610402 25615000 A561554C ./.K./M(.//.s +0070 00000008 D6C6C6C622 C5E30000						
+0160 00000080 D6C6C6E2 C5E30008 D6C6C6E2 C5E30088 D6C6C6E2 C5E30088 D6C6C6E2 C5E30014 D0000000 D0000008 D6C6C6E2 D6C6C6E2 D6C6C6E2 C5E30014 D0000000 D6C6C6E2 D6C6C6						
Helio 00000000 00000000 00000000 000000	+00E0	256154D2	2561D4C0	25615610	A561554C	./.K./M{./v/.<
+0110 00000004 00000000 00000008 D6C6C6E2	+00F0	80000008	D6C6C6E2	C5E30004	00000004	OFFSET
Helize CSE3006C 00000004 00000000 00000008 CSE30014 000000004 00000000 00000000 00000000	+0100	00000000	80000008	D6C6C6E2	C5E30008	OFFSET
+0130	+0110	00000004	00000000	80000008	D6C6C6E2	OFFS
+0140 00000008 D6C6C6E2 C5E30014 00000004	+0120	C5E3000C	00000004	00000000	80000008	ET
+0140 00000008 D6C6C6E2 C5E30014 00000004	+0130	D6C6C6E2	C5E30010	00000004	00000000	OFFSET
+0150 00000000 00000008 D6C6C6E2 C5E30018 +0160 00000004 00000000 000000008 D6C6C6E2 +0170 C5E3001C 00000001 04000000 00000000 +0190 08D6C6C6 E2C5E300 24000000 01000000 +0190 08D6C6C6 E2C5E300 24000000 01000000 +0190 08D6C6C6 E2C5E300 24000000 00000000 +0100 00006C6 C6E2C5E3 0022000 0000000 .0FFSET						
Holfo						
+0170						
+0180 E2C5E300 20000000 04000000 0000000 SET						
+0190						
+01A0 0008D6C6 C6E2C5E3 00280000 000A09D4 OFFSET						
+01B0 E8E2E2D3 D9C9D5C7 00000008 D6C6C6E2 +01C0 C5E3002C 000000004 00000008 00000008 +01D0 D6C6C6E2 C5E30030 00000008 0000002A5 +01E0 25649488 00000008 D6C6C6E2 C5E30004 +01F0 000002A5 308202A1 308202AA A0030201 +0200 02020100 30000669 2A864886 F7000101 +0210 05050030 4D310B30 09060355 04061302 +0220 55533118 30160603 55040A13 0F4D5920 +0230 434F4D50 414E592C 20494E43 31243022 +0240 06035504 0B131848 554D414E 20524553 +0250 4F555243 45532043 45525449 46494341 +0260 5445301E 170D3031 30363038 30353030 +0270 30305A17 0D323030 36313030 34353935 +0280 395A304D 310B300 906035504 06130255 +0290 53311830 16060355 040A130F 4D592043 +0240 4F4D5041 4E592C2 0494E43 1243022 +0240 6355040 B1318485 54D414E2 0524553 +0260 5445301E 170D3031 30363938 30353030 +0270 30305A17 0D323030 36313030 34353935 +0280 395A304D 310B3009 06035504 06130255 +0290 53311830 16060355 040A130F 4D592043 +0200 4530819F 30000609 2A864886 F70D0101 +02E0 01050003 818D0030 81890281 810083E1 +02F0 D36F32A3 1ED16837 8EF47012 0F74E1F7 +0310 4984F141 E44ABSE0 F180DC82 75216B53 4014(.) +0320 6FE7AC57 D73D4ECD 16161537 E5E786A1 7x45.;i +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 4x47 +0330 6FE7AC57 D73D4ECD 16161537 E5E786A1 7x47 +0330 6FE7AC57 D73D4ECD 16161537 E5E786A1 7x47 +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 4x47 +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 4x47 +0350 B4AA789D 54FD84F2 12798011 C767CCC d266. +0360 26EE3ED4 013BD21F AEBF8D74 6AE50203 M.K7 +0370 010001A3 81993081 80304806 09551D0F 40300 04040302 0006300F 6063551D 0F0101FF 40300 04040302 0006300F 6063551D 130101FF 40400 52E787D4 440200D 60692A86 4886F70D 44040302 0006300F 6063551D 130101FF 40400 04040302 00063818 005EEECE 337B3893 4x4444444						
+01C0 C5E3002C 00000004 00000000 00000008						
+01D0 D6C6C6E2 C5E30030 00000008 000002A5						
+01E0 25649488 00000008 D6C6C6E2 C5E30004 +01F0 000002A5 308202A1 308202A1 A0030201 +0200 02020100 300D0609 2A864886 F70D0101 +0210 05050030 4D310830 09060355 04061302 +0220 55533118 30160603 55040A13 0F4D5920 +0230 434F4D50 414E592C 20494E43 31243022						
+01F0 000002A5 308202A1 3082020A A0030201						
+0200 02020100 300D0609 2A864886 F70D0101f.ff7 +0210 05050030 4D310B30 09060355 04061302	+01E0	256494B8	80000008	D6C6C6E2	C5E30004	
+0210 05050030 4D310B30 09060355 04061302	+01F0	000002A5	308202A1	3082020A	A0030201	v.b.~.b
+0220 55533118 30160603 55040A13 0F4D5920	+0200	02020100	300D0609	2A864886	F70D0101	f.f7
+0220 55533118 30160603 55040A13 0F4D5920	+0210	05050030	4D310B30	09060355	04061302	(
+0230	+0220	55533118	30160603	55040A13	0F4D5920	
+0240 06035504 0B131B48 554D414E 20524553						
+0250 4F555243 45532043 45525449 46494341 +0260 5445301E 170D3031 30363038 30353030 +0270 30305A17 0D323030 36313030 34353935 +0280 395A304D 310B3009 06035504 06130255 +0290 53311830 16060355 040A130F 4D592043 +02A0 4F4D5041 4E592C20 494E4331 24302206 +02B0 0355040B 131B4855 4D414E20 5245534F +02C0 55524345 53204345 52544946 49434154 +02D0 4530819F 300D0609 2A864886 F70D0101 +02E0 01050003 818D0030 81890281 8100B3E1 +02F0 D36F32A3 1ED16837 8EF47012 0F74E1F7 +0300 CA9BA924 456081F5 6A5EDD89 35CA9674 +0310 4984F141 E44AB5E0 F1B0DC82 75216B53 +0320 6FE7AC57 D73D4ECD 16161537 E5E786A1 +0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A +0350 B4AA789D 54FD84F2 1279B011 C767CCCC +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 +0370 010001A3 81903081 8D304B06 09551D0F +0380 0186F842 010D043E 133C4765 6E657261 +0380 74656420 62792074 68652053 65637572 +0300 04040302 00066300F 0603551D 0F0101FF +03B0 72766572 20666F72 204F532F 33393020 +03F0 04040302 0006300F 0603551D 0F0101FF +03B0 04040302 00066300F 0603551D 0F0101FF +03B0 04040302 0006300F 0603551D 0F0101FF +03B0 040453003 0101FF30 1D060355 1D0E0416 +03F0 0414D79A 44A60457 328E9635 E655137D +0400 52E787D4 46D2300D 06092A86 4886F70D XgM.Kf.f7. +0410 01010505 00038181 0052EECE 33783893aa #.1 +0420 1989D568 AD725205 C97C4DE5 C16D13E3 .N,I@(VA_T						
+0260 5445301E 170D3031 30363038 30353030						
+0270 30305A17 0D323030 36313030 34353935						i '
+0280 395A304D 310B3009 06035504 06130255						
+0290 53311830 16060355 040A130F 4D592043						
+02A0 4F4D5041 4E592C20 494E4331 24302206 (&++ +02B0 0355040B 131B4855 4D414E20 5245534F						
+02B0 0355040B 131B4855 4D414E20 5245534F						
+02C0 55524345 53204345 52544946 49434154 +02D0 4530819F 300D0609 2A864886 F70D0101 +02E0 01050003 818D0030 81890281 8100B3E1 +02F0 D36F32A3 1ED16837 8EF47012 0F74E1F7 +0300 CA9BA924 456081F5 6A5EDD89 35CA9674 +0310 4984F141 E44AB5E0 F1B0DC82 75216B53 +0320 6FE7AC57 D73D4ECD 16161537 E5E786A1 ?X. P.+. VXf~ +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 < V. ¬.M +0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A +0350 B4AA789D 54FD84F2 1279B011 C767CCCC +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 +0370 010001A3 81903081 8D304B06 09551D0F +0380 0186F842 010D043E 133C4765 6E657261 .f8/ +0390 74656420 62792074 68652053 65637572 +03A0 65576179 20536563 75726974 79205365 +03B0 72766572 20666F72 204F532F 33393020 +03C0 28524143 4629300E 0603551D 0F0101FF +03D0 04040302 0006300F 0603551D 130101FF +03E0 04053003 0101FF30 1D060355 1D0E0416 +03F0 0414D79A 44A60457 328E9635 E655137D .P. w. o. W. ' +0400 52E787D4 46D2300D 06092A86 4886F70D .XgM.Kf.f7 +0410 01010505 00038181 0052EECE 337B3893 aa. #.1 +0420 19B9D56B AD725205 C97C4DE5 C16D13E3 .N, I@(VA_T						
+02D0 4530819F 300D0609 2A864886 F70D0101 af.f7 +02E0 01050003 818D0030 81890281 8100B3E1 aai.aa +02F0 D36F32A3 1ED16837 8EF47012 0F74E1F7 L?.t.J47 +0300 CA9BA924 456081F5 6A5EDD89 35CA9674 za5.;i.o. +0310 4984F141 E44AB5E0 F1B0DC82 75216B53 .d1.U¢.\1.b.,. +0320 6FE7AC57 D73D4ECD 16161537 E5E786A1 ?XP.+VXf~ +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 <zv¬.m< td=""> +0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A 2c.W,K. +0350 B4AA789D 54FD84F2 1279B011 C767CCCC d2G +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 M.KV. +0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8 ./ +0380 727</zv¬.m<>						
+02E0 01050003 818D0030 81890281 8100B3E1 a.ai.aa +02F0 D36F32A3 1ED16837 8EF47012 0F74E1F7 L?.t.J47 +0300 CA9BA924 456081F5 6A5EDD89 35CA9674 za5;;i.o. +0310 4984F141 E44AB5E0 F1B0DC82 75216B53 .d1.U¢.\1.b.,. +0320 6FE7AC57 D73D4ECD 16161537 E5E786A1 ?XP.+VXf~ +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 <z.v¬.m< td=""> +0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A 2c.W,K. +0350 B4AA789D 54FD84F2 1279B011 C767CCCC .d2G +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 .M.KV. +0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8/ +0380 72766572 20666F72 204F532</z.v¬.m<>						
+02F0 D36F32A3 1ED16837 8EF47012 0F74E1F7 L?.t.J47 +0300 CA9BA924 456081F5 6A5EDD89 35CA9674 za5;;i.o. +0310 4984F141 E44AB5E0 F1B0DC82 75216B53 .d1.U¢.\1.b +0320 6FE7AC57 D73D4ECD 16161537 E5E786A1 ?XP.+VXf~ +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 <z.v¬.m< td=""> +0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A 2c.W,K. +0350 B4AA789D 54FD84F2 1279B011 C767CCCC .d2G +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 M.KV. +0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8/ +0380 72766572 20666F72 204F532F 33393020 / +0380 72766572 20666F72 204F532F</z.v¬.m<>						
+0300 CA9BA924 456081F5 6A5EDD89 35CA9674 +0310 4984F141 E44AB5E0 F1B0DC82 75216B53 +0320 6FE7AC57 D73D4ECD 16161537 E5E786A1 +0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 +0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A +0350 B4AA789D 54FD84F2 1279B011 C767CCCC +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 +0370 010001A3 81903081 8D304B06 09551D0F +0380 0186F842 010D043E 133C4765 6E657261 +0390 74656420 62792074 68652053 65637572 +03A0 65576179 20536563 75726974 79205365 +03B0 72766572 20666F72 204F532F 33393020 +03C0 28524143 4629300E 0603551D 0F0101FF +03D0 04040302 0006300F 0603551D 0F0101FF +03E0 04053003 0101FF30 1D060355 1D0E0416 +03F0 0414D79A 44A60457 328E9635 E655137D +0400 52E787D4 46D2300D 06092A86 4886F70D +0410 01010505 00038181 0052EECE 337B3893 +0420 19B9D56B AD725205 C97C4DE5 C16D13E3 .N,I@(VA_T	+02E0	01050003	818D0030	81890281	8100B3E1	
+0310 4984F141 E44AB5E0 F1B0DC82 75216B53	+02F0	D36F32A3		8EF47012	0F74E1F7	
+0320 6FE7AC57 D73D4ECD 16161537 E5E786A1	+0300	CA9BA924	456081F5	6A5EDD89	35CA9674	
+0330 4C0A09A9 1464E572 35AD5F9C D40F1B55 <.z.V.¬.M	+0310	4984F141	E44AB5E0	F1B0DC82	75216B53	.d1.U¢.\1b,.
+0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A .2.c.W.,K. +0350 B4AA789D 54FD84F2 1279B011 C767CCCC d2G +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 M.KV. +0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8 // +0390 74656420 62792074 68652053 65637572 // +03A0 65576179 20536563 75726974 79205365 / +03B0 72766572 20666F72 204F532F 33393020 +03C0 28524143 4629300E 0603551D 0F0101FF +03E0 04040302 0006300F 0603551D 130101FF +03F0 0414D79A 44A60457 328E9635 E655137D <td>+0320</td> <td>6FE7AC57</td> <td>D73D4ECD</td> <td>16161537</td> <td>E5E786A1</td> <td>?XP.+VXf~</td>	+0320	6FE7AC57	D73D4ECD	16161537	E5E786A1	?XP.+VXf~
+0340 45FDF230 B0228334 E6ED2A0A 6B3AD28A .2.c.W.,K. +0350 B4AA789D 54FD84F2 1279B011 C767CCCC d2G +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 M.KV. +0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8 // +0390 74656420 62792074 68652053 65637572 // +03A0 65576179 20536563 75726974 79205365 / +03B0 72766572 20666F72 204F532F 33393020 +03C0 28524143 4629300E 0603551D 0F0101FF +03E0 04040302 0006300F 0603551D 130101FF +03F0 0414D79A 44A60457 328E9635 E655137D <td>+0330</td> <td>4C0A09A9</td> <td>1464E572</td> <td>35AD5F9C</td> <td>D40F1B55</td> <td><zv¬.m< td=""></zv¬.m<></td>	+0330	4C0A09A9	1464E572	35AD5F9C	D40F1B55	<zv¬.m< td=""></zv¬.m<>
+0350 B4AA789D 54FD84F2 1279B011 C767CCCC d2G +0360 26EE3ED4 013BD21F AEBFB074 6AE50203 M.KV +0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8/ +0390 74656420 62792074 68652053 65637572 +03A0 65576179 20536563 75726974 79205365 / +03B0 72766572 20666F72 204F532F 33393020 +03C0 28524143 4629300E 0603551D 0F0101FF +03B0 04040302 0006300F 0603551D 130101FF +03E0 04053003 0101FF30 1D060355 1D0E0416 +03F0 0414D79A 44A60457 328E9635 E655137D P.wo.W' +0410 01010505 00038181 0052EECE 337B3893 +0420 1989D56B AD725205	+0340	45FDF230	B0228334	E6ED2A0A	6B3AD28A	
+0360 26EE3ED4 013BD21F AEBFB074 6AE50203 M.KV. +0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8 / +0390 74656420 62792074 68652053 65637572 + +03A0 65576179 20536563 75726974 79205365 ./ + +03B0 72766572 20666F72 204F532F 33393020 + +03C0 28524143 4629300E 0603551D 0F0101FF - +03D0 04040302 0006300F 0603551D 130101FF - +03E0 04053003 0101FF30 1D060355 1D0E0416 - +03F0 0414D79A 44A60457 328E9635 E655137D +0400 52E787D4 46D2300D 06092A86 4886F70D .XgM.K		B4AA789D	54FD84F2			
+0370 010001A3 81903081 8D304B06 09551D0F ta.a +0380 0186F842 010D043E 133C4765 6E657261 .f8/ +0390 74656420 62792074 68652053 65637572 +03A0 65576179 20536563 75726974 79205365 ./ +03B0 72766572 20666F72 204F532F 33393020 +03C0 28524143 4629300E 0603551D 0F0101FF +03D0 04040302 0006300F 0603551D 130101FF +03E0 04053003 0101FF30 1D060355 1D0E0416 +03F0 0414D79A 44A60457 328E9635 E655137D +0400 52E787D4 46D2300D 06092A86 4886F70D .XgM.Kff.7 +0410 01010505 00038181 0052EECE 337B3893						
+0380 0186F842 010D043E 133C4765 6E657261 .f8						
+0390 74656420 62792074 68652053 65637572 +03A0 65576179 20536563 75726974 79205365 ./						
+03A0 65576179 20536563 75726974 79205365 /`						
+03B0 72766572 20666F72 204F532F 33393020 +03C0 28524143 4629300E 0603551D 0F0101FF +03D0 04040302 0006300F 0603551D 130101FF +03E0 04053003 0101FF30 1D060355 1D0E0416 +03F0 0414D79A 44A60457 328E9635 E655137D P.wo.W' +0400 52E787D4 46D2300D 06092A86 4886F70D .XgM.Kf.f7 +0410 01010505 00038181 0052EECE 337B3893 #.1 +0420 19B9D56B AD725205 C97C4DE5 C16D13E3						
+03C0 28524143 4629300E 0603551D 0F0101FF						
+03D0 04040302 0006300F 0603551D 130101FF						
+03E0 04053003 0101FF30 1D060355 1D0E0416 +03F0 0414D79A 44A60457 328E9635 E655137D .P.wo.W' +0400 52E787D4 46D2300D 06092A86 4886F70D .XgM.Kf.f7. +0410 01010505 00038181 0052EECE 337B3893aa#.1 +0420 19B9D56B AD725205 C97C4DE5 C16D13E3,I@(VAT						!!!
+03F0 0414D79A 44A60457 328E9635 E655137DP.wo.W' +0400 52E787D4 46D2300D 06092A86 4886F70D .XgM.Kf.f7. +0410 01010505 00038181 0052EECE 337B3893aa#.1 +0420 19B9D56B AD725205 C97C4DE5 C16D13E3N,I@(VAT						1
+0400 52E787D4 46D2300D 06092A86 4886F70D .XgM.Kf.f7. +0410 01010505 00038181 0052EECE 337B3893aa#.1 +0420 19B9D56B AD725205 C97C4DE5 C16D13E3N,I@(VAT						
+0410 01010505 00038181 0052EECE 337B3893aa#.1 +0420 19B9D56B AD725205 C97C4DE5 C16D13E3N,I@(VAT						
+0420 19B9D56B AD725205 C97C4DE5 C16D13E3,I@(VAT						
						aa#.1
+0430 1EEA02E6 D00A29B1 CA6490CC 0ABAD5B9 W}				C97C4DE5	C16D13E3	
	+0430	1EEA02E6	D00A29B1	CA6490CC	0ABAD5B9	W}N.

```
95E207D5
+0440
      6C61F417
                           CBE8B84B
                                      1A7BD22A
                                                  %/4.nS.N.Y...#K.
+0450
      E3BC0154
                 FDE66400
                           8A4BB3DA
                                      0D75D127
                                                  T....J.
+0460
      079743F5
                 00ED5E58
                           DC4B1FF9
                                      2937C930
                                                   .p.5..;....9..I.
                                                  T....o.*..y.¬en.
                           BE80A812
+0470
      E306B662
                 0096DD5C
                                      5F859566
+0480 15D86B0C
                 ECF12799
                           A58E813B
                                      94FDF51E
                                                   .Q,..1.rv.a.m.5.
+0490
      45D9C3E2
                 27C64C2E
                           BD000000
                                      A8C1C3C5
                                                   .RCS.F<....yACE
                 A8020000
+04A0 C5FF0000
                           00000000
                                      00000000
                                                   E...y.....
                                                   ..WEBSERV .IMWEB
+04B0
      0007E6C5
                 C2E2C5D9
                           E54005C9
                                      D4E6C5C2
+04C0
      40404001
                 01050116
                           3FC9D4E6
                                      C5C2E2D9
                                                     .....IMWEBSR
       E5000000
                 00000000
                           00000000
                                      00404040
+04D0
                                                   ٧.....
+04E0
       40404040
                 40000000
                           00000000
                                      00000000
                                                       . . . . . . . . . . .
+04F0
      00000000
                 00404040
                           40404040
                                      40000000
      00009FDF
+0500
                 90000000
                           00009FFA
                                      78000000
+0510
      00009FFA
                 E0000000
                           00010116
                                      3F000000
                                                   ....\......
+0520
      00002000
                 00000000
                           00000000
                                      00000000
                                                   . . . . . . . . . . . . . . . . . . .
+0530
      00000000
                 00009FFB
                           48000000
                                      00000000
      00009FFD
                 70000000
                           50500120
                                      040000C0
+0540
                                                   00000000
+0550
      00000000
                 00000000
                           00000000
                                                   . . . . . . . . . . . . . . . . . . .
+0560
       0000000
                 00000000
                           0000000
                                      0000000
                                                   +0570
      00000000
                 00000000
                           00000000
                                      00000000
                                                   . . . . . . . . . . . . . . . .
                                                   .....WEBSERV
+0580
      00000000
                 00000000
                           00E6C5C2
                                      E2C5D9E5
                                                   IMWEB ....ACE
                                      90C1C3C5
+0590
      40C9D4E6
                 C5C24040
                           40000000
+05A0
      E7030000
                 00000000
                           00000000
                                      00000000
                                                  Χ.....
+05B0
      00000000
                 00000000
                           00000000
                                      00000000
                                                   . . . . . . . . . . . . . . . . . . .
                                      00000000
+05C0
      00000000
                 24009FE0
                           08000000
                                                   +05D0
      0000000
                 00000000
                           00000000
                                      00000000
                                                   +05E0
      00000000
                 007F8770
                           40000000
                                      0000000
                                                   ....."g. ......
       00000000
                 00000000
                           00000000
                                      00000000
+05F0
                                                   . . . . . . . . . . . . . . . . . . .
+0600
       0000000
                 0000000
                           0000000
                                      00000000
                                                   . . . . . . . . . . . . . . . .
+0610
       00000000
                 00000000
                           00000000
                                      00000000
                                                   . . . . . . . . . . . . . . . . . . .
      00000000
                 00000000
                           00000000
                                      00000000
+0620
                                                   . . . . . . . . . . . . . . . .
+0630
      00
```

DataGetNext

The resulting example output is the same as a DataGetFirst example.

DataAbortQuery

Your results may contain a certificate. This particular DataAbortQuery follows a DataGetNext that failed because there were no certificates are in the key ring.

key ning.					
D6C6C6E2 Area leng	th:		00000004	OFFSET	
Area valu 256157D8 Area leng	th:		8000000	./.Q	
Area valu					
D6C6C6E2				OFFSET	
Area leng			00000014		
Area valu					
00000000	00000000	00000000	00000000		
00000000					
Area leng			8A000000		
Area valu					
C1C3C5C5	FF0000A8	02000000	00000000	ACEEy	
00000000	07E6C5C2	E2C5D9E5	4005C9D4	WEBSERV .IM	
E6C5C240	40400101	0501163F	C9D4E6C5	WEBIMWE	
C2E2D9E5	0000000	00000000	00000000	BSRV	
40404040	40404040	00000000	00000000		
00000000	00000000	40404040	40404040		
00000000	009FDF90	00000000	009FFA78		
00000000	009FFAE0	00000000	0101163F		
00000000	00200000	00000000	00000000		
00000000	00000000	009FFB48	00000000		
00000000	009FFD70				
Area leng			00000050		
Area valu	e:				

SAF Trace

50012004 00000000 00000000 00000000 E6C5C2E2 Area leng Area valu	00000000 000 00000000 000 00000000 C5D9E540 C9D th:	000000 000 000000 000 000000 000 04E6C5 C24	000000 000000	EBSERV IMWEB
C1C3C5E7 00000000 00000000 00000000 00000000 0000	03000000 000 00000000 000 00000024 009 00000000 7F8 00000000 000 00000000 000 00000000 000 th:	000000 000 0FE008 000 000000 000 077040 000 000000 000 000000 000 000000 000 000000	000000	"g.
+0000 00000 +0010 D7D6E +0020 00000 +0030 A616A +0040 00000 +0050 00000 +0060 00F55 +0070 00000	2E3 00000000 000 00000000 852 00000000 000 00000000 000 00000000 C80 00000000	C3C54040 00000000 00000000 00000000 0000000	D6D4E5E2 00000000 00000000 4040000 0000000 000000	RTRACE OMVS POST w.yq 5*5*
+0080 C2E2D +0090 009FF +00A0 84F95 +00B0 00000 +00C0 25615 +00D0 25615 +00E0 25615 +00F0 00000	9E5 00000000 DC0 00000000 A2C 00000000 01F 00000029 600 256155F4 608 256155FC 4D2 2561D4C0	009FFDC0 00000000 00000000 00000034 25615604 256154D1 25615610 C5E30004	00000000 B5F9F4C7 00000000 2561D0C0 256155F8 2561560C A5615790 00000004	BSRV94G d9!/}{ .//.4.//.8 .//.J.//.K./M{./v/
+0100 00000 +0110 00000 +0120 C5E30 +0130 D6C6C +0140 00000 +0150 00000 +0160 00000 +0170 C5E30	000 00000008 004 00000000 00C 00000004 6E2 C5E30010 008 D6C6C6E2 000 00000008 004 00000000	D6C6C6E2 00000000 00000000 00000004 C5E30014 D6C6C6E2 00000008 03000000	C5E30008 D6C6C6E2 00000008 00000000 00000004 C5E30018 D6C6C6E2 08D6C6C6	OFFSETOFFS ET OFFSETOFFSETOFFSETOFFS ETOFF
+0180 E2C5E +0190 08D6C +01A0 0008D +01B0 E8E2E +01C0 C5E30 +01D0 D6C6C +01E0 00000 +01F0 00000	300 20000000 6C6 E2C5E300 6C6 C6E2C5E3 2D3 D9C9D5C7 02C 00000004 6E2 C5E30030 008 D6C6C6E2	0400000 2400000 00280000 00000008 00000000 00000004 C5E30000 00000000	00000000 01000000 000A09D4 D6C6C6E2 00000008 256157D8 00000014 00000000	SET
+0200 00000 +0210 02000 +0220 E2C5D +0230 05011 +0240 00000 +0250 00000 +0260 40404 +0270 00000	000 000000A8 000 00000000 9E5 4005C9D4 63F C9D4E6C5 000 00000000 000 00000000 040 40404040	C1C3C5C5 00000000 E6C5C240 C2E2D9E5 40404040 00000000 00000000	FF0000A8 07E6C5C2 40400101 00000000 40404040 00000000 009FDF90 009FFAE0	yACEEyWEB SERV .IMWEBIMWEBSRV
+0280 00000 +0290 00000 +02A0 009FF +02B0 00000 +02C0 00000 +02D0 00000 +02E0 00000 +02F0 00000	000 0101163F 000 00000000 B48 00000000 050 50012004 000 00000000 000 00000000 000 00000000	0000000 00000000 00000000 0000000 000000	00200000 00000000 009FFD70 00000000 00000000 00000000 00000000 C9D4E6C5	

+0300	C2404040	00000090	C1C3C5E7	03000000	BACEX
+0310	00000000	00000000	00000000	00000000	
+0320	00000000	00000000	00000000	00000024	
+0330	009FE008	00000000	00000000	00000000	\
+0340	00000000	00000000	00000000	00000000	
+0350	7F877040	00000000	0000000	00000000	"g
+0360	00000000	00000000	00000000	00000000	
+0370	00000000	00000000	0000000	00000000	
+0380	00000000	00000000	0000000	00000000	
+0390	00000000	00000000	00000000		

Using the trace to find problems

If SSL doesn't start, or starts but SSL handshake does not occur, turn on trace and restart the web server. Calls to r_datalib occur when the web server is being started. You should be able to tell from this list what went wrong based on the trace you received. For these trace examples, important trace information will be followed by an explanatory note.

First DataGetFirst contains a return code of 8 with a reason code of 54
 All of the trace results offset 8 are not shown. The sample trace follows:

Area value: D6C6C6E2 C5E30010		OFFSET	
Note: Offset 10 is the return coo	de		
Area length: Area value: 00000008	00000004	·	I
Note: Hex 8 in the return code	value		
Area length:	80000000		
Area value: D6C6C6E2 C5E30014 Area length:	00000004	OFFSET	I
Area value: 00000000 Area length:	00000008	····	I
Area value: D6C6C6E2		OFFSET	
Note: Offset 18 is the reason co	ode		
D6C6C6E2 C5E30018 Area length: Area value:	00000004	OFFSET	I

Note: Hex 54 is the reason code value

00000054

54 in hex is equal to a reason code of 80 which for this function is reason: Profile for ring_name not found. The next step for fixing this problem would be to look at the trace at offset 28 and compare the ring name found there with the one in the keyfile area of the .conf file. An example of output at offset 28 is the first DataGetFirst previous example. Check that the ring name is correct. Note, ring names are case sensitive and must be owned by the web server daemon user ID (WEBSRV by default). This can be checked using the RACDCERT LISTRING TSO command.

SSL doesn't start on the server and there are no traces.
 Check the keyfile like in the http.main.conf file. It should look like this:

|

keyfile MYSSLRING SAF

If the SAF positional parameter is missing, then System SSL treats the name as a GSKKYMAN key file, not a RACF keyring, hence there will be no trace. If the keyfile really is a RACF keyring, add the SAF positional parameter.

Second DataGetNext has a reason code 2C.

Hex 2C is reason code 44: Record not found. This means that there is a problem with one of the two certificates attached to the ring. To find out what exactly is wrong, some more research is needed.

In order for SSL to function properly the key ring needs:

- to be owned by the ID who assigned to the web server process
- to contain a signing CERTAUTH certificate with CERTAUTH usage
- to contain a PERSONAL certificate owned by the ID who is assigned to the web server process. This certificate must also be signed by the CERTAUTH certificate and be marked DEFAULT.
- to have neither certificate marked NOTRUST

To learn what could be wrong at this point a RACDCERT should be issued: RACDCERT ID(webserver-user-id) LISTRING(MYSSLRING)

WEBSERV is the name of the ID who assigned to the web server process. MYSSLRING is the name listed in the keyfile area of the .conf file. The output should be similar to this example:

Ring:

MANAGE BENG

>MYSSLRING<			
Certificate Label Name	Cert Owner	USAGE	DEFAULT
MY PKI CA	CERTAUTH	CERTAUTH	NO
SSL CERT	ID(WEBSERV)	PERSONAL	YES

Looking at this output will verify most of the these conditions.

The output: "IRRD114I Ring MYSSLRING does not exist." indicates that the ring in the .conf file doesn't exists, or that it is not owned by the ID assigned to the web server process.

To check the signer of the PERSONAL certificate is the CERTAUTH certificate and that neither certificate is marked NOTRUST, other commands must be used.

Using the previous certificate label names, the commands and output are listed:

Command:

```
RACDCERT ID(WEBSERV) LIST(LABEL('SSL CERT'))
```

Output:

```
Label: SSL CERT
Certificate ID: 2QfmxcLixdn14uLTQMPF2eNA
Status: TRUST
Start Date: 2001/06/25 00:00:00
End Date: 2002/06/25 23:59:59
Serial Number:
    >01<
Issuer's Name:
    >OU=HUMAN RESOURCES CERTIFICATE.O=MY COMPANY, INC.C=US<
Subject's Name:
    >CN=WWW.MYCOMPANY.COM.O=MY COMPANY INC.L=MILLBROOK.SP=NEW YORK.C=US<
Private Key Type: Non-ICSF
Private Key Size: 1024
Ring Associations:
```

Command:

RACDCERT CERTAUTH LIST(LABEL('MY PKI CA'))

Output:

Label: MY PKI CA Certificate ID: 2QiJmZmDhZmjgdToQNfSyUDDwUBA Status: TRUST Start Date: 2001/06/08 00:00:00 End Date: 2020/06/09 23:59:59 Serial Number: Issuer's Name: >OU=HUMAN RESOURCES CERTIFICATE.O=MY COMPANY, INC.C=US< Subject's Name: >OU=HUMAN RESOURCES CERTIFICATE.O=MY COMPANY, INC.C=US< Key Usage: CERTSIGN Private Key Type: Non-ICSF Private Key Size: 1024 Ring Associations: Ring Owner: WEBSERV Ring: >MYSSLRING<

Note: Both certificates have TRUST status and the PERSONAL certificate was issued by the CERTAUTH certificate.

Compare your results with the examples provided to evaluate you situation for common IBM HTTP Server related problems related to an incorrect SAF keyring configuration. If you need additional assistance when you are done, you may want to consider calling the IBM support center.

SAF Trace

Chapter 3. Reporting RACF problems to IBM

Prerequisites

See Troubleshooting the problem and the diagnostic procedures for this type of problem.

You also need to understand the procedures for reporting a problem to the IBM support center.

Introduction to reporting RACF problems to IBM

This describes the information that you need to collect before you report any RACF problems to IBM. The procedure lists only the information that the IBM support center is most likely to request.

When you report a problem, you need to describe your system and the problem that you experienced. The people at the IBM support center use this information to see whether your problem is already known to IBM and to check whether a fix is available.

Note: If you have the Information/MVS or Information/Access product, or a similar problem-search tool, you can do checking for a duplicate known problem yourself. Performing a preliminary search for a matching problem and Searching for a matching problem have advice on which RACF symptoms to use in search arguments for search tools.

If you report a new, unique problem, you need to provide additional problem information.

How to report RACF problems to IBM

Before calling IBM, collect the information called for in the worksheet for your type of problem. See Figure 4 through Figure 12 for the applicable worksheet.

Consider collecting all the information on the worksheets before reporting the problem, to speed up your phone conversation if the support center needs the information.

The support center people usually want you to provide the information in the same order as in the checklist.

Recommendations

- Before you call, you need to have a listing or an interactive display ready that shows any problem information that you obtained from a system dump or another data set.
- For the most efficient phone conversations with IBM, consider having IPCS (Interactive Problem Control System) ready for interactive dump displays during the conversation. Formatting a system dump has advice about using IPCS.

© Copyright IBM Corp. 1994, 2008

Procedure

For the complete list of diagnostic procedures for each type of problem, see Troubleshooting tables for problems in RACF.

	Information to Gather before Calling IBM with Abend Problems
You	ı can use this worksheet to write on directly or as a guide for making your own notes elsewhere.
	Level of z/OS: (Example: z/OS Version 1 Release 1)
	RACF is enabled for sysplex communication:
	non-data sharing mode
	data sharing mode
	read-only mode
3.	System is configured as an RRSF node:
	local mode
	remote mode
4.	PTF level of abending module: (Example: UW27135)
	Installation exits installed (which exits are used and what they do):
6.	User modifications, if any (which modules are modified and what the modifications do):
7.	Any recent changes (such as maintenance applied, Security Server options changed, new program products, new hardware):
8.	A formatted system dump with options: SUMMARY SUMDUMP FORMAT CURRENT TRACE LOGDATA LPAMAP CPUDATA SYMPTOMS
9.	The message that contains the abend code: Complete message text:
10.	Assembler listing, if source is available.
11.	If a hardware problem is suspected, EREP (error recording and editing program) records.
Figu	re 4. Information to Gather before Calling IBM with Abend Problems
	Information to Gather before Calling IBM with Documentation Problems
	can use this worksheet to write on directly or as a guide for making your own notes elsewhere.
	Level of z/OS: (Example: z/OS Version 1 Release 1)
	RACF is enabled for sysplex communication:
	non-data sharing mode the sharing mode
	data sharing mode
0	• read-only mode
	System is configured as an RRSF node:
	• local mode
	• remote mode
	Installation exits installed (which exits are used and what they do):
	User modifications, if any (which modules are modified and what the modifications do):
	Publication title and order number (with dash level):
1.	Page number or topic number:

Figure 5. Information to Gather before Calling IBM with Documentation Problems

	Information to Gather before Calling IBM with Output Problems
	can use this worksheet to write on directly or as a guide for making your own notes elsewhere.
1.	Level of z/OS: (Example: z/OS Version 1 Release 1)
2.	RACF is enabled for sysplex communication:
	non-data sharing mode
	data sharing mode
	read-only mode
3.	System is configured as an RRSF node:
	local mode
	remote mode
4.	Installation exits installed (which exits are used and what they do):
5.	User modifications, if any (which modules are modified and what the modifications do):
6.	Any recent changes (such as maintenance applied, RACF options changed, new program products, new hardware):
7.	Description of RACF request that caused incorrect output (who did it—user's attributes, routine running, or both—and what was done):
8.	IBM reference material that explains what correct output should look like:
9.	Online or printed copy of output, or other indications that the output is incomplete:
10.	If available, please attach example of good output (before problem occurred).
11.	If a report writer problem, please attach a listing of the SMF (system management facilities) records.

Figure 6. Information to Gather before Calling IBM with Output Problems

Procedure

	Information to Gather before Calling IBM with Logon Problems
	can use this worksheet to write on directly or as a guide for making your own notes elsewhere. e: Before filling out this worksheet, make sure the users are not "revoked".
1.	Level of z/OS: (Example: z/OS Version 1 Release 1)
2.	RACF is enabled for sysplex communication:
	non-data sharing mode
	data sharing mode
	read-only mode
3.	System is configured as an RRSF node:
	local mode
	remote mode
4.	Installation exits installed (which exits are used and what they do):
5.	User modifications, if any (which modules are modified and what the modifications do):
6.	Any recent changes (such as maintenance applied, RACF options changed, new program products, new hardware):
7.	How many users cannot log on?
8.	Are there any aspects that the users having logon problems share, such as group memberships or authorities?
9.	When users attempt to log on, what message, if any, is displayed?
10.	If applicable, have SMF records related to the logon problem available.

Figure 7. Information to Gather before Calling IBM with Logon Problems

	Information to Gather before Calling IBM with Loop Problems						
Υοι	You can use this worksheet to write on directly or as a guide for making your own notes elsewhere.						
	Level of z/OS: (Example: z/OS Version 1 Release 1)						
	RACF is enabled for sysplex communication:						
	non-data sharing mode						
	data sharing mode						
	read-only mode						
3.	System is configured as an RRSF node:						
	• local mode						
	remote mode						
4.	Installation exits installed (which exits are used and what they do):						
	5. User modifications, if any (which modules are modified and what the modifications do):						
	6. Any recent changes (such as maintenance applied, RACF options changed, new program products, new hardware):						
7.	What external symptoms indicate that there is a loop (such as multiple copies of output or poor performance)?						
	Description of routines involved in loop, with addresses of instructions, if available:						
	What conditions the loop occurs in:						
	Whether loop is enabled or disabled.						
	If loop is enabled, please include a standalone system dump.						
	If applicable, please have available online or (preferably) printed output.						
Figu	Information to Gather before Calling IBM with Loop Problems Information to Gather before Calling IBM with Message Problems						
	3						
Υοι	can use this worksheet to write on directly or as a guide for making your own notes elsewhere.						
1.	Level of z/OS: (Example: z/OS Version 1 Release 1)						
2.	RACF is enabled for sysplex communication:						
	non-data sharing mode						
data sharing mode							
read-only mode							
3.	System is configured as an RRSF node:						
	local mode						
	remote mode						
4.	Installation exits installed (which exits are used and what they do):						
5.	User modifications, if any (which modules are modified and what the modifications do):						
6.	Any recent changes (such as maintenance applied, RACF options changed, new program products, new hardware):						
7.	Complete message text, including any related messages that immediately precede or follow it:						
8.	Name of routine running when message is issued:						

Figure 9. Information to Gather before Calling IBM with Message Problems

Procedure

Information to Gather before Calling IBM with Performance Problems						
Υοι	u can use this worksheet to write on directly or as a guide for making your own notes elsewhere.					
	Level of z/OS: (Example: z/OS Version 1 Release 1)					
	RACF is enabled for sysplex communication:					
	non-data sharing mode					
	data sharing mode					
	read-only mode					
System is configured as an RRSF node:						
٥.	local mode					
	remote mode					
4	Installation exits installed (which exits are used and what they do):					
	User modifications, if any (which modules are modified and what the modifications do):					
	Any recent changes (such as maintenance applied, RACF options changed, new program products, new					
0.	hardware):					
7.	Description of the conditions in which degradation occurs:					
	Any console messages (please attach).					
Ü	ure 10. Information to Gather before Calling IBM with Performance Problems					
	Information to Gather before Calling IBM with Return Code Problems					
Υοι	u can use this worksheet to write on directly or as a guide for making your own notes elsewhere.					
	Level of z/OS: (Example: z/OS Version 1 Release 1)					
	RACF is enabled for sysplex communication:					
۷.	non-data sharing mode					
	data sharing mode					
	read-only mode					
3	System is configured as an RRSF node:					
Ο.	local mode					
	remote mode					
4.						
4. 5.						
	 User modifications, if any (which modules are modified and what the modifications do): Any recent changes (such as maintenance applied, RACF options changed, new program products, new 					
0.	hardware):					
7.	The return code you expected:					
	The return code you received:					
8.	The RACF macro request that caused the return code (including the parameters passed):					
9.	The order number (with dash level) and page number or topic number of your copy of the document in which you found the description of the return code:					
	Order number: Page number or topic number:					
10	Assembler listing of program					

Figure 11. Information to Gather before Calling IBM with Return Code Problems

Information to Gather before Calling IBM with Wait Problems						
You can use this worksheet to write on directly or as a guide for making your own notes elsewhere.						
1. Level of z/OS: (Example: z/OS Version 1 Release 1)						
2. RACF is enabled for sysplex communication:						
non-data sharing mode						
data sharing mode						
read-only mode						
3. System is configured as an RRSF node:						
local mode						
remote mode						
4. Installation exits installed (which exits are used and what they do):						
5. User modifications, if any (which modules are modified and what the modifications do):						
. Any recent changes (such as maintenance applied, RACF options changed, new program products, new hardware):						
7. PSW (program status word):						
3. Source and assembler listing of routine in which wait occurred, if available.						

Figure 12. Information to Gather before Calling IBM with Wait Problems

Chapter 4. Troubleshooting your RACF database

This topic describes the organization of the RACF database and explains how you can troubleshoot and repair it by using some of the RACF utilities.

You can get a better understanding of the contents of your RACF database by running the database unload utility, IRRDBU00. If you unload your RACF database to a sequential file (using the IRRDBU00 utility), you might uncover problems in your database that you find only when reading the profile. This utility reads every profile.

For more information on using the IRRDBU00 utility, see *z/OS Security Server RACF Macros and Interfaces* and *z/OS Security Server RACF Security Administrator's Guide*.

You might also find it advantageous to use the IRRUT200 RACF database verification utility program to assist in locating problems in your RACF database. For more details, see *z/OS Security Server RACF System Programmer's Guide*.

Format of the RACF database

This describes the format of the RACF database.

Each RACF database is a non-VSAM single extent data set that is made up of 4KB blocks and must be cataloged.

A RACF database consists of several types of records:

Header block (inventory control block, ICB)

Is the first block in a RACF database and provides a general description of the database.

Templates

Contain mappings of the entity records for the RACF database.

Segment table block

Contains mappings of individual segments from within a template.

BAM (block availability mask) blocks

Determine allocation of space within the RACF database.

Index blocks

Locate entity records (profiles) in the RACF database.

If you are using application identity mapping and it is in stage 1, 2, or 3, there will be an alternative alias index to consider. This alias index correlates an application identity (a set field defined within a non-base segment within the RACF templates, such as the OMVS UID field) to a base profile (the user or group profile which has an application identity field set to a particular value).

Profiles (entity records)

Contain descriptions of the attributes and authorities for every entity defined to RACF. These entities are:

- User profiles
- Group profiles
- DASD data set profiles

Profiles for resources defined by entries in the class descriptor table

Figure 13 illustrates the format of the database.




Figure 13. Format of the RACF Database

The first byte in each block is an identifier. Possible values you might use to locate blocks are:

- X'02'—segment table
- X'00'—BAM
- X'83'-data
- X'8A'—index
- · X'C3'-empty block

Header block (ICB)

The ICB (inventory control block) has a relative byte address of zero. RACF uses the ICB to locate the other blocks in a RACF database. Each RACF database has an ICB, but RACF uses only the ICB for the master primary data set when determining the setting of options.

See Appendix A, "The Inventory Control Block (ICB)" for the fields shown in the data area, ICB.

Templates

IRRTEMP2 contains database profile mappings. When your installation creates the database, IRRMIN00 reads the mappings, formats them, and writes them to the RACF database.

RACF provides a template for each type of profile (user, group, data set, and general resource). Each profile consists of a BASE segment, plus other potential segments, for example, the DFP segment. In turn, each template contains a number that corresponds to the type of profile that it is mapping. The template maps the fields that are contained in each segment of the profile by describing the field name and field length.

If a template block is continued into another block, the last three bytes of the template block will contain the block number of the template expansion block. This figure illustrates how the templates would look if Template 2 expanded into Block xxx of the database:




Figure 14. Template blocks

Attention

Do not modify the template definitions that IBM supplies, or unpredictable results might occur.

Segment table block

The segment table block contains mappings of individual segments from within a template. These describe the segments associated with the profiles.

BAM blocks

A block availability mask (BAM) block is a 4KB block that describes the availability of the corresponding blocks in a RACF database. Each BAM block starts with a header followed by a table of two-byte "block masks".

The BAM high-water mark contained in the ICB is the address of the BAM block from which segments were last allocated or deallocated. This BAM block is used first when starting a search for space for a new allocation.

BAM block header

The BAM block header contains this information:

Bytes Description

Bytes 0-5:

Relative byte address (RBA) of the previous BAM block (or 0 if this is the first block).

RBA of the next BAM block (or 0 if this is the last block).

Bytes 12-17:

RBA of the first 4KB block whose space this BAM block defines.

Bytes 18-19:

Number of 4KB blocks whose space this BAM block defines. This is also the number of two-byte block masks which follow. A BAM block can correspond to a maximum of 2038 blocks of 4096 bytes each.

BAM block masks

Following the BAM block header is a table of block masks. A block mask is a two-byte field (16 bits) that corresponds to one 4KB block in the RACF database. The first block mask corresponds to the block whose RBA is defined in Bytes 12-17 of the BAM header. Subsequent block masks in the BAM correspond successively to the 4KB blocks following this RBA. Bytes 18-19 of the BAM header contains the number of block masks in this BAM.

Database format

Each bit in the block mask corresponds, successively, to a 256-byte slot within the mask's corresponding 4KB block. If a bit is set to 1, its corresponding slot in the block is free. Otherwise, this slot is in use. Figure 15 is an example of a block mask for a block whose first six slots are in use.




Figure 15. Block Masks of the RACF Database

Index blocks

RACF uses a multilevel index set to locate profiles. There can be up to 10 levels on a RACF database. All index searches begin with the highest level index block, whose RBA (relative byte address) is contained in the ICB (inventory control block). At every level but the lowest, the first entry in a block that is equal to or alphabetically greater than the requested profile name is used to reach the next lower-level index block. If no entry is greater than or equal to the profile name, the index search continues with the RBA pointed to by the last index entry in the block being searched. This situation can occur because of previous index-entry deletions.

The lowest level of index blocks (level 1) is known as the sequence set. Index entries in the sequence set contain the RBAs of the actual profile segments. Each block then points to the next block in succession.

Note: The pointer in the ICB that is pointing to the first block in the sequence set is for use by BLKUPD if the database index structure is corrupted. The sequence set pointer is also used by IRRUT400 when reorganizing the database.

Figure 16 is an example of part of a RACF index, and it illustrates the path RACF uses to find the profile named FAL.N. This example assumes 3 levels. The level-1 blocks for the first and third level-2 blocks are partially shown in the figure.




Figure 16. Example of a RACF Index

Alias index blocks

A companion to the existing index structure is the alias index structure. For alias indices, there are four notable differences to consider:

- · There are alternate anchors in the ICB
- · There is a new format identifier
- · There is a new index entry identifier
- The index entries in the sequence set of the alias index contain a base profile data area that names the base profile that corresponds to the particular alias index.

Overview

An index block (regular or alias) is a 4KB block whose overview is composed of these parts:

Database format

- Header
- · Table of index entries.
- · Sequence set chain pointer entry. For level-1 index blocks only. Follows last index entry.
- X'0C' Delimiter
- (At end of block) Table of two-byte offsets to the index entries.

Figure 17 is an example of an overview of a level-1 index block. The first 14 bytes is the header. In this example, n (in the header) is the number of index entries. Offset X'0EF8' is the sequence set chain pointer entry (which follows the last index entry). This offset value is also found in the header.




Figure 17. Example Overview of a Level-1 Index Block

Index block header

The format of an index block header in the index block is as follows:

Bytes Description

Byte 0:

X'8A' Index block identifier

Bytes 1-2:

X'1000' Length of the index block

Byte 3:

X'4E' Index block identifier

Byte 4:

X'00' Format identifier for regular index block; X'01' Format identifier for alias index block

Byte 5:

Index-level number (01-0A)

Bytes 6-7:

Offset to the last entry in the index block. In a level-1 index block, the last entry is a sequence set chain pointer entry. In an upper-level index block, the last entry is the last index entry of the block.

Bytes 8-9:

Offset to free space in the index block

Bytes 10-11:

Offset to a table of index-entry offsets

Bytes 12-13:

Count of index entries in the block. This is also equivalent to the count of entries in the table of index-entry offsets (the bottom part of the block).

Figure 18 shows an example of the index block header set up for the example of the level-1 index block in Figure 17.




Figure 18. Example of an Index Block Header

Index entries

Following the index block header is a table of index entries. The format of an index entry is:

Bytes Description

Byte 0:

Entry identifier, as follows:

X'21' Normal index entry (non-duplicate entry). In a set of duplicate index entries, this identifier marks the last index entry of the set.

X'22' Duplicate index entry. This entry is a duplicate of the next index entry. Index entries can be duplicates of one another until one marked by the X'21' identifier is reached.

A duplicate index entry can exist only in a level-1 index block and only for data set profiles with the same name.

X'23' Alias index entry.




Figure 19. Example Overview of an Alias Index Block

Byte 1:

Type of profile for this index entry, as follows:

X'01' Group

X'02' User

X'04' Data set

X'05' General resource

Bytes 2-3:

Length of this index entry

Bytes 4-5:

Offset from the beginning of the entry to the segment data area for regular index entries, and offset from the beginning of the entry to the base profile data area for alias index.

Bytes 6-7:

Front-end compression count. Number of leftmost characters that had been suppressed from the profile name in the index entry's name field. To save space in the database, RACF suppresses the leftmost characters that are identical to those in the preceding index entry.

To find the suppressed characters, trace the index entries backward to the one with front-end compression count of zero. In this index entry, all leftmost characters would still be intact in its name field.

The first index entry of the index block always has a front-end compression count of zero. A name that is exactly the same as one in the previous entry might be totally compressed.

Figure 20 shows an example of front-end compression counts.




Figure 20. Example of Front-End Compression in an Index Block

Note: Not all entry names are necessarily compressed at all times. For example, when a new name is added, it might not be compressed until the database is reformatted (such as through the IRRUT400 utility).

Bytes 8-9:

Length of index entry name

Bytes 10-11:

Reserved

Bytes 12-*n*:

Index entry name, 0-255 bytes. Bytes 8-9 contain the actual length.

An index entry name corresponds to either a profile name or application identity, but it does not always match letter by letter or byte by byte. It might have been compressed (see Bytes 6-7, for example), or some of its characters might have been substituted by RACF for internal purposes (such as to save space or to facilitate the search).

For an alias index entry, the first 3 bytes of the entry name are non-EBCDIC and specifies the particular alias field within the template as follows:

- Byte 0: Template identifier. Describes the type of base profile associated with this alias entry.
- Byte 1: Segment identifier. See Table 20.
- **Byte 2**: Field identifier. See the template descriptions in *z/OS Security Server RACF Macros and Interfaces* for field identifiers.

In an upper-level (that is, not level 1) index block, the index entry name might correspond to the entry name of the last index entry of the next-lower level block. Its rightmost characters might have been compressed if RACF determines that they are not essential to finding the correct index block at the next-lower block.

An index entry name of 255 bytes of X'FF' signifies the end of index blocks for that level number.

Database format

Bytes *n*+1:

Segment data area. In an upper-level regular or alias index block, the segment data area has this format:

Byte 0:

X'62' Identifier byte

Bytes 1-6:

RBA of the next-lower-level index block

In a regular level-1 index block, the segment data area has this format: Byte 0:

> Number of segment-data fields in this data area. This is also the number of segments in this profile.

Bytes 1-7:

Segment-data field. This field is repeated successively for each segment in the profile. The format of a segment-data field is:

Byte 0:

Segment Identifier. See Table 20 for a list of identifiers. Profile type is indicated in Byte 1 of the index entry.

Bytes 1-6:

RBA of the segment.

In an alias level-1 index block, the segment data area has this format:

Bytes 0-1:

Number of base profile fields in this data area.

Bytes 2–*n*:

Base profile data field. This field is repeated successively for each base profile reference for this application identity.

Bytes 2-3

Denotes the 1–8 character length of the user or group profile name immediately following this field.

Bytes 4-m:

Base profile name.

Table 20. Segment Identifiers

Group	User	Data Set	General
X'01'—BASE X'02'—DFP X'03'—OMVS X'04'—OVM X'05'—TME X'06'—CSDATA	X'01'—BASE X'02'—DFP X'03'—TSO X'04'—CICS X'05'—LANGUAGE X'06'—OPERPARM X'07'—WORKATTR X'08'—OMVS X'09'—NETVIEW X'0A'—DCE X'0B'—OVM X'0C'—LNOTES X'0D'—NDS X'0E'—KERB X'0F'—PROXY X'11'—CSDATA	X'01'—BASE X'02'—DFP X'03'—TME	X'01'—BASE X'02'—SESSION X'03'—DLFDATA X'04'—SSIGNON X'05'—STDATA X'06'—SVFMR X'07'—CERTDATA X'08'—TME X'09'—KERB X'04'—PROXY X'0B'—EIM X'0C'—ALIAS X'0D'—CDTINFO X'0E'—ICTX X'0F'—CFDEF

Figure 21 shows an example of a normal index entry in a level-1 index block for a user profile named USR26, which contains three segments: Base, TSO, and DFP.




Figure 21. Example of Index Entry for USR26 with a Base, TSO, and DFP Segment

Sequence set chain pointer entry

A sequence set chain pointer entry is an entry that references to the next level-1 index block. This entry follows the last index entry of the index block and is applicable only in level-1 index blocks. It has this format:

Bytes Description

Bytes 0-1:

X'2066' Sequence Set Chain Pointer Entry Identifier

Bytes 2-7:

RBA of next level-1 index block (0 if last one of the set)

An example of a sequence set chain pointer entry is illustrated in Figure 17.

X'0C' delimiter

A 1-byte X'0C' delimiter marks the end of the list of entries in an index block. In an upper-level index block, it follows the last index entry. In a level-1 index block, it follows the sequence set chain pointer entry.

The X'0C' delimiter is then followed by a series of zeros until the beginning of the table of index-entry offsets at the end of the block.

Index-Entry offset table

At the end of an index block is a table of two-byte offsets to the index entries. This table starts from the bottom of the block and grows inward so that the last offset of the table is the offset for index entry 1, the next-to-last offset of the table is for index entry 2, and so on. RACF uses this table to perform a search on index entries.

In the example in Figure 17, note that the last offset of the table is the offset of the first index entry and the first one of the table is the offset of the last index entry.

Profiles

The profiles, or entity records, contain the actual descriptions of the attributes and authorities for every entity (users, groups, DASD data sets, and resource classes defined in the class descriptor table) defined to RACF. The number in the entry-type field identifies the type of profile and corresponds to the number of the template that maps this type of profile.

The record data (including the type of profile that it is) follows the header. This data consists of the fields that are mapped by a template. See the template description

Database format

corresponding to each type of profile for the contents of these fields. The template descriptions are in *z/OS Security Server RACF Macros and Interfaces*.

Because there can be duplicate entry names in different classes, the RACF manager adds a class identifier to the beginnings of general-resource entry names (for example; DASDVOL -, TAPEVOL -, or TERMINAL- for DASD volumes, tape volumes, or terminals, respectively). General-resource class names that are not eight characters in length are padded with trailing blanks.

Note: If you define a profile and use generic characters such as (*) to add members to the profile, RLIST RESGROUP does not return any of the matching profiles in its output because it does not support generic matches.

Generic profile names have the first period in a DATASET profile replaced by X'01', and the dash in the class identifier for general-resource classes replaced by X'02'. Although these expanded names are transparent to the user, they appear when using the block update utility command or the IRRUT200 utility. You also need to be aware of them when constructing a database range table.

When a tape volume profile is initially created, RACF places the tape volume serial in the volume list of the profile. RACF creates an index entry and profile name in the standard way. If another tape volume is to be added (creating a volume set), RACF adds its volume serial to the volume list in the profile and creates an index entry for the volume that points to the profile.

For example, if there are six tape volumes in a tape volume set, there are six index entries pointing to the same profile and six volume serials in the profile's volume list. When a tape volume is deleted, RACF removes the volume serial from the volume list in the profile and deletes the index entry. The profile name does not change, even if the volume after which the profile might have been named is deleted.

It is possible to have a profile name of TAPEVOL -TAPE01 without having a corresponding index entry and without having TAPE01 in the volume serial list.

The database profiles consist of segments that are made up of fields and repeat groups that follow a record header. The record header, the field structure, and the repeat group structure are described in this document.

Record header

The record header consists of these fields:

Bytes Description Byte 0: X'83' Record identifier. **Bytes 1-4:** Physical length of this record, in bytes. Logical record length. Length, in bytes, of the portion of the **Bytes 5-8:** record that actually contains data. Bytes 9-16: Segment name. Bytes 17-18: Length of profile name (in Byte 20). **Byte 19:** Reserved

Bytes 20+n: Profile name. Its length is specified in Bytes 17-18.

Field structure

Following the record header is a set of one or more segment data fields. Although the potential total length of these fields is 2GB, that might be limited by the type of DASD and the amount of virtual storage available to the user.

All data fields are in a variable-length format. The first byte is the field ID. See the template descriptions in z/OS Security Server RACF Macros and Interfaces for field identifiers. Where indicated in the template descriptions, the field can be a member of a repeat group.

If the field is not a member of a repeat group, the field ID is followed by a field indicating the length of the data that follows. If the high-order bit of the length field is zero, this field is one byte and the data can be up to 127 bytes; if the high-order is set, the length field is 4 bytes (for example, X'80000022'), and the data can be up to 2 to the 31st power.

This figure shows the structure of a profile field when the length field is one byte. The structure is:



where:

- i is the field ID. i is 1 byte.
- / is the length of the data that follows. / is 1 byte.
- The high-order bit of this field is zero.
- data is 1 to 127 bytes of data.

This figure shows the structure of a profile field when the length field is 4 bytes. The structure is:



where:

- *i* is the field ID. *i* is 1 byte.
- I is the length of the data that follows. I is 4 bytes.
- The high-order bit of this field is set to one.
- data is up to 2³¹ bytes of data.

· Repeat group structure

A repeat group structure contains a set of fields that are part of a repeat group. It contains all occurrences of a repeat group and, for each occurrence, it contains the count of fields and every field in the occurrence, *including those with null values*.

The field ID (first byte) is associated with the entire repeat group. Fields in a repeat group structure do not have individual ID fields.

Each repeat group is limited to 64KB of installation data.

The structure of a repeat group is:



where:

Database format

- i is the field ID. i is 1 byte.
- / is the length of the entire repeat group. / is 4 bytes.
- *m* is the count of repeat group occurrences. *m* is 4 bytes.
- c1, c2, and c3 are counts of fields in each occurrence. Each is 1 byte.
- a1, a2, and b2 are data, up to 2^{31} bytes each.

Each data field has this format:



where:

- / is the length of data that follows. If its high-order bit is zero, / is one byte and the data length can be up to 127 bytes. If its high-order bit is set to one, / is 4 bytes.
- data is up to 2³¹ bytes of data.

When displaying a profile with the BLKUPD command, you might want to have the RACF database templates available for reference. These can be found in z/OS Security Server RACF Macros and Interfaces. They include a list of the field IDs in numeric order. The field IDs are in decimal in z/OS Security Server RACF Macros and Interfaces but in hexadecimal when displayed by the BLKUPD command.

Example of a profile

Figure 22 shows a profile and identifies the record header, the first profile field structure, and the first repeat group structure. The field IDs of the other fields are shaded. You can use BLKUPD to display a profile. See Block Update command for a RACF database (BLKUPD).




Figure 22. Example of a Profile Displayed by BLKUPD

Database Unload Utility for a RACF Database (IRRDBU00)

If you plan to use the block update (BLKUPD) command to update your database, you might want to get a better understanding of what your current database looks like.

The database unload utility (IRRDBU00) reads every profile as it unloads your RACF database to a sequential file. This can uncover problems in your database that you find only when reading the profile.

For more information on using the utility, see *z/OS Security Server RACF Macros* and *Interfaces* and *z/OS Security Server RACF Security Administrator's Guide*.

Note: RACF creates a member HWM for the SECDATA CATEGORY profile, which is reserved for IBM's use. The HWM member and a corresponding 0503 record exist if you have added any categories to the SECDATA CATEGORY profile. Deleting the record will impact RACF behavior.

Block Update command for a RACF database (BLKUPD)

You can use BLKUPD to examine or modify any block in a RACF database: a data block, index block, BAM block, or unallocated block.

In order to use BLKUPD you must have at least UPDATE authority to the RACF database.

Attention

If you are sharing a RACF database between a z/OS V1R8 system and a z/OS V1R4 system, do not run this utility from the z/OS V1R4 system. You should run it from z/OS V1R8, or from a z/OS V1R5, V1R6, or V1R7 system with APAR OA12443 installed.

Before using the BLKUPD command, you should be very familiar with the RACF database and its configuration, because using BLKUPD improperly can damage the RACF database. (See Format of the RACF database.)

Before entering the BLKUPD command, you should read and understand the format of the database. Then, before using the BLKUPD command to perform updates to your RACF database, try to use one of the other RACF commands to alter or delete the entry in question.

This describes the following topics:

- Considerations when using the BLKUPD command
- · Hierarchy and uses of the BLKUPD command
- Examples

Considerations for using BLKUPD

The following considerations apply to using the block update command (BLKUPD):

- · In general:
 - Do not use BLKUPD during hours of peak activity on the active RACF database because the command uses hardware RESERVES or enqueues (GRS ENQs) to serialize access to the database.
 - BLKUPD can only be issued as a TSO command.
 - BLKUPD cannot be directed to run on another system using the AT or ONLYAT keywords or automatic command direction.
 - Whenever you need to run BLKUPD against a database that is active on a system that is a member of the RACF sysplex data sharing group, always run the utility from a system in the group, and make sure you use the real name of the dataset and not an alias. If you do not, you might damage your RACF database, or receive unpredictable results from the utility.
- Before using BLKUPD:
 - Try to correct the error by using other RACF commands.
 - Make a copy of the RACF database. Use BLKUPD on the copy. IBM might be able to use the copy for further diagnosis.
 - Run IRRUT200. The output might be useful in identifying the damaged portion of the database.
- · Document all changes made for future reference and diagnosis.
- RVARY the "repaired" database online and test your fix.

- After the fix has been verified, apply the fix to the "real" database and RVARY this database ONLINE.
- If a profile is in question, delete the index entry that points to the profile, rather than trying to repair the profile itself. Use a RACF command to add the profile and index entry.
- Do not use BLKUPD to modify the BAM blocks. Instead, run the IRRUT400 utility, which rebuilds the BAM blocks.
- If a RACF database is RACF-protected, you must have at least UPDATE authority to the database.
- When executing BLKUPD under control of command procedures, you must add the DATA and ENDDATA command procedure statements around each BLKUPD command and subcommand that is also a command procedure statement. See z/OS TSO/E Command Reference for a description of command procedures.
- When executing BLKUPD under a TMP (terminal monitor program) that allows multitasking, you cannot have any other active task in your session. Allow the BLKUPD command to complete before executing any other TSO command.
- BLKUPD does not support attention handling. If an attention interrupt occurs and the user does not enter any data other than a null line or TIME command, the RACF database remains enqueued.
- The subcommands of BLKUPD follow the TSO syntax rules. See z/OS TSO/E Command Reference for a description of TSO command syntax rules.
- · BLKUPD runs as an APF-authorized TSO command.
- · TSO prompt must be set on.
- When RACF is enabled for sysplex communication, you cannot use BLKUPD to update the database if your system is operating in read-only mode.

If you need assistance in using BLKUPD, contact the IBM support center.

Hierarchy of the BLKUPD command

Figure 23 shows the relationship between the BLKUPD command and its levels of subcommands.




Figure 23. The Relationship between the BLKUPD Command and Its Levels of Subcommands

Using the BLKUPD command

Use the BLKUPD command to access the RACF database. Do not use BLKUPD during hours of peak activity on the active RACF database because the command uses hardware RESERVES or enqueues (GRS ENQs) to serialize access to the database.

```
The Syntax of the BLKUPD command
 BLKUPD [racfbname]
```

where racfbname specifies the name of a data set in the RACF database. The name can be from 1 to 44 characters.

If the name is not specified, the RACF database must be allocated to the TSO session with the SYSRACF file name.

Working with the RACF database: To update or examine a data set in the RACF database, perform the following steps:

1. Decide which data set in the RACF database you want to work with, and enter BLKUPD.

Note: After entering the BLKUPD command, you can use the following subcommands: LOCATE, READ, or END.

- 2. Decide which block on the database you want to work with. If needed, use the LOCATE subcommand to assist you in finding the specific block.
- 3. Enter the READ subcommand, specifying either UPDATE or NOUPDATE.
- 4. Enter the subcommands of READ necessary to accomplish your task.
- Issue the END command to end the utility.

Note that ALIAS index blocks are not supported by this utility. It is possible to use the LIST and the REP subcommands with ALIAS index blocks but great care should be taken since there is no format checking.

For more information on the alias indices, see Alias index blocks.

The LOCATE subcommand: Use the LOCATE subcommand when you do not know the relative byte address (RBA) of the block you want to address. This subcommand locates an index entry in the sequence set and displays a formatted list of the contents of the level-1 index block containing the entry name. Optionally, the LOCATE subcommand displays a listing of all the index blocks in the chain from the highest-level index block to the appropriate level-1 block.

The syntax of the LOCATE subcommand (of BLKUPD)

LOCATE ENTRY (entryname) CLASS(classname) [GENERIC] [LISTALL]

where:

ENTRY(entryname)

specifies the index entry to be located; entryname can be from 1 to 255 characters, which can be enclosed in quotation marks or not, and can contain hexadecimal data. For example:

ENTRY(I X'C2' MUSER)

is equivalent to:

ENTRY (IBMUSER)

To specify a mixed-case entry name, you must enclose entryname in quotes. If you do not enclose *entryname* in quotes, alphabetic characters in *entryname* are treated as uppercase characters, regardless of the case in which you enter them. For example, if you enter:

LOCATE ENTRY(irrsitec) CLASS(USER)

RACF looks for the index entry IRRSITEC, but if you enter:

LOCATE ENTRY('irrsitec') CLASS(USER)

RACF looks for the index entry irrsitec.

CLASS(classname)

is one of the following:

- GROUP
- USER
- DATASET
- The class name of the general resource

GENERIC

specifies that *entryname* is generic.

LISTALL

specifies that all the index blocks in the hierarchy chain are to be displayed.

Database format

The formatted list contains the same information as that produced by the FORMAT subcommand of READ (see The FORMAT subcommand).

If an index block in the chain contains an error, BLKUPD produces a hexadecimal dump of the block. If the name is not found in a level-1 block, BLKUPD displays the block that should contain it.

If the block containing the name is not found by a hierarchy index search because of errors in the chain, BLKUPD searches the sequence set.

The READ subcommand: The READ subcommand reads the block specified by the RBA (relative block address) into storage and copies it into a work area.

This subcommand allows you to examine or change the database.

The syntax of the READ subcommand (of BLKUPD)

READ rba [UPDATE] [NOUPDATE]

where:

rba

specifies the relative byte address of the block to be read.

If the RBA does not represent an address on a 4KB boundary, the block on the 4KB boundary that contains the RBA is read. You can enter the RBA value as a hexadecimal (X'nn') or decimal (nnn) number. Hexadecimal numbers can be from 1 to 8 characters; decimal numbers can be from 1 to 10 characters.

UPDATE

specifies you are planning to update one of the blocks in the RACF database.

Specifying the UPDATE keyword imposes an exclusive RESERVE on the database, meaning the issuing system has exclusive control of the RACF database and only that system can update it. Any system that shares the database cannot read the database or update it. In addition, no other user on the issuing system can read or update the database.

If RACF is enabled for sysplex communication:

- 1. You cannot update the RACF database when you are operating in read-only
- 2. When running in data sharing mode, RACF uses global resource serialization (ENQ/DEQ), rather than hardware RESERVEs.

NOUPDATE

specifies you are examining one of the blocks in the RACF database.

Specifying the NOUPDATE keyword imposes a shared RESERVE on the RACF database, meaning that if you are sharing the RACF database with another system, both systems can read the database, but neither system can update it.

The NOUPDATE keyword on the READ command permits you to examine the database block without making any changes. NOUPDATE is the default. Should you make changes and then end BLKUPD, the changes are not recorded.

If RACF is enabled for sysplex communication and running in data sharing mode, RACF uses global resource serialization (ENQ/DEQ) rather than hardware RESERVEs.

Using the subcommands of READ: The UPDATE keyword on the READ subcommand allows you to use the subcommands to update the block. The subcommands are:

- LIST—displays portions of the block in hexadecimal.
- FORMAT—produces a formatted listing of the contents of an index block.
- FIND—locates the offset of data in the block.
- REP—replaces data in the block (valid only with the UPDATE command).
- DISPLAY—displays the entries of an index block one at a time (it has several subcommands associated with it).
- REREAD—overlays the new block in the work area with the old block (valid only with the UPDATE keyword).
- END—terminates the READ function.

The FIND subcommand: The FIND subcommand finds the hexadecimal offset of a string in the block.

Syntax of the FIND subcommand of READ FIND string [OLD] [NEW]

where:

string

specifies the string that is to be located.

The string can be hexadecimal (which is specified as X'string') or characters (which can be enclosed in quotation marks or not). Hexadecimal strings are right-justified and padded with zeros to a byte boundary. Character strings are left justified and padded with zeros to a byte boundary.

If *string* contains lowercase characters, *string* must be enclosed in quotation marks. If string is not enclosed in quotation marks, all characters are treated as uppercase characters, regardless of the case in which you enter them.

OLD

specifies the original block obtained by the READ command. OLD is the default.

NEW

specifies the copy of the block. NEW is valid only with the READ UPDATE function.

After entering the FIND subcommand, enter the LIST subcommand to see the actual data.

The LIST subcommand: The LIST subcommand displays a hexadecimal dump of all or part of the RACF block. It allows you to see exactly what is inside the block and where it is located.

```
Syntax of the LIST Subcommand of READ
 LIST [NEW|OLD]
      RANGE(xx,yyy)
      ALL
```

where:

NEW

specifies the copy of the original block (it might or might not have been updated). NEW is valid only with the READ UPDATE function.

OLD

specifies the original block that was copied into storage when you entered the READ command. OLD is the default.

RANGE

defines the parts of the block to be listed.

- xxx specifies the offset into the block where the listing is to start. The default is 0.
- yyy specifies the number of bytes to be listed. The default is 16.

The values for xxx and yyy can be hexadecimal or decimal numbers. If the sum of xxx and yyy exceeds 4096, the dump ends at the end of the block.

ALL

specifies a hexadecimal listing of the entire RACF block.

The FORMAT subcommand: The FORMAT subcommand displays a formatted list of the contents of an index block. Use the FORMAT subcommand if you have read an index block and need to see the all the entries in this block and their RBAs (relative block addresses).

The list contains the following information:

- · The RBA of the block
- · The level of the block
- · The offset to the last entry
- · The offset to free space
- The offset of each entry within the block
- · The front-end compression count of each entry
- The name of each entry (generic names are identified by a G in parentheses after the name)
- · The last qualifier encode byte of each entry
- The RBA of the next-level index block for each entry or, for level-1 blocks, the RBA of the profile

If the block obtained by the READ command is not a valid index block, the request is rejected.

Syntax of the FORMAT subcommand of READ -

FORMAT [OLD NEW]

where:

OLD

specifies the original index block obtained by the READ command. OLD is the default.

NEW

specifies the index block that was updated. NEW is valid only with the READ **UPDATE** function.

The REP subcommand: The REP subcommand replaces a string in the new block with another string. Optionally, this subcommand verifies the original string before making the replacement. This subcommand is valid only with the READ **UPDATE** function.

Syntax of the REP subcommand of READ UPDATE

REP new-string OFFSET(xxx)[VER(old-string)]

where:

new-string

specifies the new string of data.

The data can be hexadecimal (which is specified as X'string') or characters (which can be enclosed in quotation marks or not). Hexadecimal strings are right-justified and padded with zeros to a byte boundary. Character strings are left-justified and padded with zeros to a byte boundary.

If new-string contains lowercase characters, new-string must be enclosed in quotation marks. If new-string is not enclosed in quotation marks, all characters are treated as uppercase characters, regardless of the case in which you enter them.

OFFSET(xxx)

specifies the offset into the block where the string is to be replaced.

VER(old-string)

specifies the original string that is to be verified. If the string is not found at offset xxx into the new block, the replacement is not made.

If old-string contains lowercase characters, old-string must be enclosed in quotation marks. If you do not enclose *old-string* in quotation marks, all characters are treated as uppercase characters, regardless of the case in which you enter them.

Note: The verify (VER) operand only verifies the characters specified; it does not verify the whole string. Be sure to enter the entire string you want verified.

The DISPLAY subcommand: The DISPLAY subcommand displays an entry of the index block that was read by the READ command.

When you enter the DISPLAY subcommand (after specifying READ UPDATE), the BLKUPD command copies the original block to a new block in storage. This copy is referred to as a **new** index block. You can then use the DELETE, CHANGE, and INSERT subcommands of the DISPLAY subcommand to modify the displayed entries.

If the block obtained by the READ command is not a valid index block, RACF rejects your DISPLAY request.

Syntax of the DISPLAY subcommand of READ

DISPLAY [ENTRY(entryname) CLASS(classname)] [GENERIC]

where:

ENTRY(entryname)

specifies the index entry where the display begins. If you do not specify an entry name, the display begins at the first entry in the index block; the entry name can be from 1 to 255 alphanumeric characters, which can be enclosed in quotation marks or not, and can contain hexadecimal data.

To specify a mixed-case entry name, you must enclose entryname in quotes. If you do not enclose entryname in quotes, alphabetic characters in entryname are treated as uppercase characters, regardless of the case in which you enter them.

If you specify an entry name, you must specify a class name.

CLASS(classname)

must be one of the following:

- GROUP
- USER
- DATASET
- · The class name of the general resource

GENERIC

indicates that the index specified in ENTRY(entryname) is a generic name.

Using the Subcommands of DISPLAY: The subcommands of the DISPLAY subcommand are:

CHANGE

Changes the displayed entry (valid only with the READ UPDATE function).

INSERT

Inserts a new index entry immediately preceding the entry that is displayed (valid only with the READ UPDATE function).

NEXT Displays the next entry.

DELETE

Deletes the displayed entry (valid only with the READ UPDATE function).

END Ends the DISPLAY function.

The CHANGE subcommand of DISPLAY: This subcommand is valid only with the READ UPDATE function.

The CHANGE subcommand allows you to change the following:

- · The name
- The RBA (relative byte address) of the index entry displayed
- The RBA of the segment specified
- The compression count (or the entry identifier byte or both)

The changed entry is displayed. Enter the NEXT subcommand or a null line to display the next entry.

Syntax of the CHANGE subcommand of DISPLAY CHANGE [ENTRY(entryname) CLASS(classname)]|[SEGMENT(segment-name)] [GENERIC] [RBA(rba)] [COMP(xx)] DUPLICATE|NODUPLICATE

where:

ENTRY(*entryname*)

specifies the index entry where the display begins. If you do not specify an entry name, the display begins at the first entry in the index block; the entry name can be from 1 to 255 alphanumeric characters, which can be enclosed in quotation marks or not, and can contain hexadecimal data.

To specify a mixed-case entry name, you must enclose *entryname* in quotes. If you do not enclose *entryname* in quotes, alphabetic characters in *entryname* are treated as uppercase characters, regardless of the case in which you enter them.

If you specify an entry name, you must specify a class name.

CLASS(classname)

must be one of the following:

- GROUP
- USER
- DATASET
- The class name of the general resource

The length of name plus the compression count cannot exceed 255. To create a fully compressed name, specify ENTRY (''), where the entry name is a null string, with a nonzero compression count. For a discussion of compression and an explanation of index blocks and encoding, see Index entries.

SEGMENT(segment-name)

specifies the segment RBA to be changed.

The BASE segment cannot be specified as the segment name.

The ENTRY and CLASS keywords and the SEGMENT keyword are mutually exclusive. If both are specified, SEGMENT is ignored.

If you specify SEGMENT, only the RBA (relative byte address) of the SEGMENT is changed.

GENERIC

indicates that the index entry name specified in ENTRY(entryname) is a generic name.

RBA(rba)

the value of *rba* can be from 1 to 8 hexadecimal characters or from 1 to 10 decimal characters.

COMP(xx)

the front-end compression count. xx is limited to one less than the length of the entry, and never exceeds 254. xx can be specified as decimal or hexadecimal characters.

DUPLICATE

means that you want to make the entry a duplicate of the entry immediately following. This entry that immediately follows might be on the same block or appear at the beginning of the next block.

NODUPLICATE

means that you do not want the current entry to be a duplicate of the entry immediately following.

There is no default on this keyword; if you do not specify DUPLICATE or NODUPLICATE, the entry identifier byte is not changed. It remains at its previous setting.

Specify only those keywords that you want to change. The others remain at their previous settings.

The BLKUPD command does not perform any checking to see if you have specified the appropriate keyword values to be changed. You must be very careful because specifying an incorrect keyword value or omitting a keyword and its value can produce unpredictable results.

The INSERT subcommand of DISPLAY: This subcommand is valid only with the READ UPDATE function.

The INSERT subcommand inserts a new index entry immediately preceding the entry that is displayed if SEGMENT is not specified. When SEGMENT is specified, the new segment ID is placed at the end of the segment array.

Note: The BLKUPD command cannot be used to insert the first entry in the database.

BLKUPD displays the new entry; entering the NEXT subcommand displays the original entry again.

```
Syntax of the INSERT subcommand of DISPLAY
INSERT [ENTRY(entryname) CLASS(classname)] | [SEGMENT(segment-name)]
       [GENERIC]
       RBA(rba)
       [COMP(xx)]
       [DUPLICATE | NODUPLICATE]
```

where:

ENTRY(entryname)

specifies the index entry where the display begins. If you do not specify an entry name, the display begins at the first entry in the index block. The entry name can be from 1 to 255 alphanumeric characters, which can be enclosed in quotation marks or not, and can contain hexadecimal data.

To specify a mixed-case entry name, you must enclose entryname in quotes. If you do not enclose entryname in quotes, alphabetic characters in entryname are treated as uppercase characters, regardless of the case in which you enter them.

If you specify an entry name, you must specify a class name.

CLASS(classname)

must be one of the following:

- GROUP
- USER
- DATASET
- · The class name of the general resource

The length of name plus the compression count cannot exceed 255. To create a fully compressed name, specify ENTRY (' '), where the entry name is a null string, with a nonzero compression count. For a discussion of compression, see Index entries.

SEGMENT(segment-name)

specifies the new segment to be inserted.

The BASE segment cannot be specified as the segment name.

The ENTRY and CLASS keywords and the SEGMENT keyword are mutually exclusive. If both are specified, SEGMENT is ignored.

GENERIC

indicates that the index specified in ENTRY(entryname) is a generic name.

RBA(rba)

the value of rba can be from 1 to 8 hexadecimal characters or from 1 to 10 decimal characters.

COMP(xx)

the front-end compression count. xx is limited to one less than the length of the entry, and never exceeds 254. xx can be specified as decimal or hexadecimal characters.

DUPLICATE

means that you want to make the entry a duplicate of the entry immediately following. This entry that immediately follows might be on the same block or appear at the beginning of the next block.

NODUPLICATE

means that you do not want the current entry to be a duplicate of the entry immediately following.

The NEXT subcommand of DISPLAY: The NEXT subcommand displays the next entry.

Syntax of the NEXT subcommand of DISPLAY (READ) NFXT N

Entering a null line also displays the next entry.

The DELETE subcommand of DISPLAY: This subcommand is valid only with the READ UPDATE function.

The DELETE subcommand deletes the current index entry or segment, and the next entry is displayed.

Attention

Before you change or delete the first entry in the index, or insert a new first entry, you must first decompress any compressed entries that follow in the index block.

The best way to decide which entries to decompress is to display the index block and then examine the names and their compression counts, paying attention to the second entry in the block. If the second entry is compressed, or does not match the first entry enough to allow for proper decompression of the following entries, you must first delete the first entry and then do the following to each entry that needs decompression:

• If the entry has a compression count, enter a CHANGE command: CHANGE COMP(0) ENTRY(xxxyyy) CLASS(classname)

where xxx is the compressed front-end characters as indicated by the old compression count, and yyy is the name that the BLKUPD command gave you as the name of this entry. (Note that you need the GENERIC keyword on the CHANGE command if the entry is generic.)

The second entry (now the new first entry) has now been changed.

- If this entry matches the old (first) entry for enough characters to decompress the remaining entries, you can stop. If it doesn't, you must decompress any entry that this new first entry does not match.
- To do so, enter NEXT commands until you get to the next entry that has to be changed. Then enter the CHANGE command to alter it as already described. Continue with the NEXT and CHANGE commands until all the entries in question have been resolved.

It might only be necessary to decompress that second entry; however, based on your examination of the listing, you might have to decompress all the entries. For an explanation of compression, see Index entries.

Syntax of the DELETE subcommand of DISPLAY

```
DELETE
          [SEGMENT(segmentname)]
D
```

where:

SEGMENT(segment-name)

deletes the specified segment from the current index entry.

The END subcommand of DISPLAY: This subcommand ends the DISPLAY subcommand.

You can continue to examine or update the block under the READ subcommand.

Syntax of the END subcommand of DISPLAY

END SAVE NOSAVE where:

SAVE

tells RACF to update the new index block to reflect the changes made under the DISPLAY subcommand. Specifying SAVE means that you want the new index block to replace the old one.

NOSAVE

tells RACF to ignore all the changes you made under the DISPLAY subcommand with the UPDATE keyword specified on the READ subcommand.

If you did n4ot specify UPDATE on the READ command, then the NOSAVE option is forced.

The REREAD subcommand: The REREAD subcommand is valid only with the READ UPDATE function.

The REREAD subcommand allows you to overlay the new RACF block in the work area with the old block. Use this function when you have made errors to the new block while using the DISPLAY or REP subcommands. This subcommand gives you a new copy of the old block.

Syntax of the REREAD subcommand of READ UPDATE REREAD

The END subcommand of READ: The END subcommand ends processing on the RACF database block that you obtained by entering the READ command.

Syntax of the END subcommand of READ END SAVE NOSAVE

where:

SAVE

specifies that you want the new block to be written back to the RACF database to replace the old one that was read.

NOSAVE

specifies that the RACF database not be updated with the new block. The NOSAVE option is forced if you did not specify the UPDATE keyword on the READ command or if you did not make any changes to the block.

If you want to use the READ function to examine or update another block, enter another subcommand.

The END subcommand of BLKUPD: The END subcommand ends BLKUPD.



If you want to read another block, do not enter this final end statement (just enter another subcommand of the BLKUPD command).

The BLKUPD command—A scenario

This example illustrates the functions of BLKUPD. It is not meant to be used for repairing your RACF database.

1. Issue the BLKUPD command on the RACF data set that you want to work with.

```
BLKUPD 'SYS1.RACF'
BLKUPD:
```

2. Replace a string in the block located at RBA X'E000'.

```
READ X'E000' UPDATE
BLKUPD:
```

reads the block at RBA X'E000' and specifies that changes are to be made to the block.

FORMAT

produces a formatted listing of the OLD index block obtained by the READ command.

		RBA OF 00000000E000				
OFFSE	T COMP	• ENTRY NAME	RBA		BAM	
	COUN	T		BLOCK	BYTE	BIT
00E	000	BEATL	0000000DC00	00	02F	4
02A	000	HILDE	0000000D000	00	02E	0
		SEGMENT NAME: TSO	00000000D900	00	02F	1
		DFP	0000000DA00	00	02F	2
051	000	HILDE.RDS.CNTL	00000000DE00	00	02F	6
073	000	IBMUSER	0000000D700	00	02E	7
08E	000	M267	00000000DB00	00	02F	3
0A6	000	M550ABC	0000000DD00	00	02F	5
0C1	000	SALES	00000000DF00	00	02F	7
0DA	000	SALES.* (G)	00000000F000	00	032	0
0F5	000	SECLABEL-SYSHIGH	0000000D100	00	02E	1
119	000	SECLABEL-SYSLOW	0000000D200	00	02E	2
13C	000	SECLABEL-SYSNONE	0000000D300	00	02E	3
160	000	SYSCTLG	00000000D600	00	02E	6
17B	000	SYS1	00000000D400	00	02E	4
193	000	VSAMDSET	00000000D500	00	02E	5
1AF	000	255 X'FF'S				
2BB		SEQUENCE SET POINTER	000000000000			
TOTAL NAMES IN THIS BLOCK-015. UNUSED BYTES-3358. AVERAGE NAME LENGTH-025.						
LEVEL NUMBER-01. DISPLACEMENT TO LAST KEY-02BB. DISPLACEMENT TO FREE SPACE-02C4						
(G) -	(G) - ENTITY NAME IS GENERIC					

3. Find the string in the old block.

```
IRR63002I Offset is X'0000009A'
BLKUPD:
```

locates the offset of the character string 'M267' in the old block.

4. Verify that offset X'9A' in the new block contains the character string 'M267' and replace that string with the character string 'M270'.

```
REP M270 OFFSET(X'9A') VER(M267)
IRR63004I REPLACE complete.
```

5. List the modified area of the new block (8 bytes beginning at offset X'9A').

```
LIST NEW RANGE(X'9A',8)00000000000000
 009A D4F2F7F0 01010000
  *M270....
```

6. Delete the first entry in the index block.

```
BLKUPD:
DISPLAY

OFFSET COMP. ENTRY NAME

COUNT

00E 000 SIVLE 00000000DC00

DELETE
```

deletes the index entry just displayed. The next entry, which moves up to replace the deleted one, is displayed.

7. Insert a new first index entry.

```
INSERT ENTRY(SIVLE) CLASS(USER) RBA(X'DC00')
```

inserts a new index entry, with the specified name and RBA immediately preceding the entry just displayed. The new entry is displayed.

```
IRR63038I The first index entry has been inserted. The rest of the index block may need to be updated.  
00E 000 SIVLE 0000000DC00 NEXT
```

displays the next index entry.

```
00E 000 HILDE 0000000D000
SEGMENT NAME: TSO 0000000D900
DFP 0000000DA00
```

8. Change the name of the entry.

```
04C 000 HILDE.RDS.CNTL 00000000DE00 CHANGE ENTRY(HILDE.RDS.CHNG) CLASS(DATASET)
```

changes the entry name of the entry.

```
04C 000 HILDE.RDS.CHNG 00000000DE00
```

Save the changes you have made and obtain a listing of your updated block.
 END SAVE

ends the DISPLAY command and saves the changes that were made in the index block. The utility still runs under the READ subcommand.

```
IRR63009I DISPLAY ended. Changes saved. FORMAT NEW
```

produces a formatted listing of the updated index block.

BLOCK V	HTIW	RBA OF 00000000E000		
OFFSET	COMP	. ENTRY NAME	RBA	BAM
	COUN	Т	BLOCK	BYTE BIT
00E	000	SIVLE	0000000DC00 00	02F 4
025	000	HILDE	00000000D000 00	02E 0
		SEGMENT NAME: TSO	00000000D900 00	02F 1
		DFP	00000000DA00 00	02F 2
04C	000	HILDE.RDS.CHNG	00000000DE00 00	02F 6
06E	000	IBMUSER	00000000D700 00	02E 7
089	000	M270	00000000DB00 00	02F 3
0A1	000	M550ABC	0000000DD00 00	02F 5
0BC	000	SALES	00000000DF00 00	02F 7
0D5	000	SALES.* (G)	00000000F000 00	032 0
0F0	000	SECLABEL-SYSHIGH	00000000D100 00	02E 1
114	000	SECLABEL-SYSLOW	00000000D200 00	02E 2
137	000	SECLABEL-SYSNONE	0000000D300 00	02E 3

Database format

```
15B 000 SYSCTLG
176 000 SYS1
                                                   00000000D600 00 02E
                                                                           6
                                                   00000000D400 00 02E
                                                                           4
18E 000 VSAMDSET
                                                   00000000D500 00 02E
                                                                           5
1AA 000 255 X'FF'S
           SEQUENCE SET POINTER
                                                   000000000000
TOTAL NAMES IN THIS BLOCK-015. UNUSED BYTES-3363. AVERAGE NAME LENGTH-024.
LEVEL NUMBER-01. DISPLACEMENT TO LAST KEY-02B6. DISPLACEMENT TO FREE SPACE-02BF
(G) - ENTITY NAME IS GENERIC
```

10. Save the changes made and write them back to the RACF database.

END SAVE IRR63013I READ ended. Block saved.

ends the READ command and writes the new block out to the RACF database.

11. Locate the block that contains the generic name of SALES.*.

LOCATE ENTRY (SALES.*) CLASS (DATASET) GENERIC

displays a formatted list of the level one block that contains the generic entry name 'SALES.*'.

BLOCK WITH RBA OF 0000000E000						
OFFSE	T COMP		RBA		BAM	
	COUN				BYTE	
00E	000	SIVLE	00000000DC00	00	02F	4
025	000	HILDE	00000000D000	00	02E	0
		SEGMENT NAME: TSO	00000000D900	00	02F	1
		DFP	0000000DA00	00	02F	2
04C	000	HILDE.RDS.CHNG	00000000DE00	00	02F	6
06E	000	IBMUSER	0000000D700	00	02E	7
089	000	M270	00000000DB00	00	02F	3
0A1	000	M550ABC	00000000DD00	00	02F	5
0BC	000	SALES	00000000DF00	00	02F	7
0D5	000	SALES.* (G)	00000000F000	00	032	0
0F0	000	SECLABEL-SYSHIGH	00000000D100	00	02E	1
114	000	SECLABEL-SYSLOW	00000000D200	00	02E	2
137	000	SECLABEL-SYSNONE	00000000D200	00	02E	3
15B	000	SYSCTLG	00000000D500	00	02E	6
176	000	SYS1	00000000D000	00	02E	4
18E	000	VSAMDSET	00000000D500	00	02E	5
1AA	000	255 X'FF'S				
2B6		SEQUENCE SET POINTER	000000000000			
TOTAL NAMES IN THIS BLOCK-015. UNUSED BYTES-3363. AVERAGE NAME LENGTH-024.						
LEVEL	LEVEL NUMBER-01. DISPLACEMENT TO LAST KEY-02B6. DISPLACEMENT TO FREE SPACE-02BF					
(G) -	(G) - ENTITY NAME IS GENERIC					

12. End the BLKUPD session.

BLKUPD: END READY

terminates the BLKUPD command.

Chapter 5. Error recovery for RACF Remote Sharing Facility (RRSF)

This topic describes:

- The flow of a directed command in a RACF remote sharing facility (RRSF) environment
- The types of errors experienced in an RRSF environment
- · Handshaking between RRSF nodes
- · The connection states of RRSF nodes and the transitions between them
- · Actions to recover from an RRSF failure
- The recording of RRSF errors

RRSF moves the RACF command between the user who initiated the command and the RACF subsystem address space where the transaction is processed (either on a local or a remote node) and moves the RACF command output between the RACF subsystem address space where the transaction was processed (on a local or a remote node) and the node where the user was logged on when the transaction was initiated.

The INMSG data set is used to temporarily hold requests that are being sent to the local node from itself or a remote node, such as commands directed to the local node or output from RACF commands that were directed to a remote node. The OUTMSG data set is used to temporarily hold requests that are being sent to a target node, such as commands directed from the local node. If RRSF experiences a failure, it:

- Detects the error when it first occurs. This:
 - Prevents additional damage to the RACF subsystem address space and the RACF database.
 - Allows either the system programmer or the IBM support center to diagnose and fix the problem.
- Protects the rest of the RRSF network from damage by isolating the error to the failing node.
- Saves the work request for retry when the error has been corrected.

Figure 24 shows an illustration of the flow of a directed command in an RRSF environment. The steps shown in this figure are:

- 1. A user issues a RACF command. This command enters the local node's OUTMSG data set while waiting to be sent to the remote node.
- When this command is sent to the remote node to be processed, it enters the remote node's INMSG data set.
- The command is processed in the remote node's RACF subsystem address space and the results are placed in the remote node's OUTMSG data set while waiting to be sent to the local node.
- 4. The results are sent to the local node and placed in the local node's INMSG data set until the output is returned to the user.

© Copyright IBM Corp. 1994, 2008




Figure 24. Flow of a Directed Command in an RRSF Environment

Types of errors in an RRSF environment

The following types of errors can be experienced by an RRSF network:

Definition errors

For RRSF, typical definition errors are local or remote nodes not being correctly defined to the system or to each other. In general, definitions need to be accurate and consistent on both the local and target node. Problems occur when there are:

- Incorrect VTAM® DEFINITIONS
- Incorrect LU names
- Down-level versions of RACF or RACF database templates
- Differences between node definitions to RACF (that is, something specified on the TARGET command at a local node was specified differently on a corresponding TARGET command at a remote node)
- Incorrect security information for APPC conversation
- Incorrect security information to access VSAM data sets
- Differences between node status (NODEA is operative while NODEB thinks NODEA is dormant).

Environmental errors

Typical environmental errors are MVS resources not being available. These can occur when MVS or RACF is being restarted or can occur because of high volumes of directed commands (including automatically directed commands) or password changes that are being synchronized. This type of error can occur on either the local or remote node, and includes:

- · VTAM not yet active
- · APPC address space not yet active
- · Insufficient main memory
- Insufficient VSAM space
- Retryable APPC errors
- Remote RACF subsystem address space not active

Program errors

Overlaid control blocks, overlaid in-storage data, or programming errors within RRSF, and the portions of RACF invoked within the RACF subsystem address space can also cause an abend. Non-fatal errors detected by RRSF can have the following symptoms:

- · Units of work being lost
- · Units of work being done multiple times
- · All tasks in the RACF subsystem address space being in wait state
- Resources are allocated to a request and the request has completed either normally or abnormally and the resources are not released or deallocated

Transmission and line errors

Transmission and line errors are external to the application, such as a car hitting a telephone pole.

Handshaking and state changes

Handshaking involves verifying that two RRSF nodes can communicate with each other and are compatible. Handshaking occurs whenever a TARGET command is issued to activate the connection between the local node and a remote node and if sufficient information has been provided. Activating a remote node connection requires sufficient information to do all of the following:

- Allocate and open the VSAM data sets (INMSG and OUTMSG data sets)
- Register the RACF subsystem address space as an APPC/MVS server
- Define the connection to the remote node (LUNAME, and optionally TPNAME and MODENAME)

Connection states of RRSF nodes

While at a high level there are two types of connections between nodes, operative and dormant, at a lower level the connection between two nodes can be in any one of a number of states.

The state of the connection between nodes and the transitions between the states used by RRSF have the following characteristics:

- Controls whether information is sent to the remote node.
- Respects the state change request of the last person who issued such a request; that is, the connection status is not changed from dormant to active without an explicit human action.
- Provides available information on how the connection reached the current state.
- Recognizes that certain state changes do not occur immediately because they need to check with the partner node to determine if the new state is allowed.

The following table shows the potential states that can exist on a local node to describe the connection between that node and a remote node:

Table 21. Connection States between Nodes

Name	Abbreviation	Description
operative pending connection	O-P-C	The local node has requested that the connection be activated and is attempting to activate the conversation. The local node has not yet received a confirmation that the remote node will accept the connection.

Handshaking and states

Table 21. Connection States between Nodes (continued)

Name	Abbreviation	Description
operative pending verification	O-P-V	The local node's request for a conversation has been accepted. The two nodes are communicating and evaluating information they have exchanged to determine if they are compatible. If the two nodes are not compatible, both nodes will remain in the operative pending verification state.
operative active	O-A	The connection between two nodes is active. The two nodes have verified that they can communicate with each other and that they are compatible with each other.
operative in error	O-E	The local system has lost the connection with the remote node. At one time a connection had been successfully established.
dormant by local request	D-L	The local node's connection with a remote node has been made dormant by an operator issuing a TARGET DORMANT command.
dormant by remote request	D-R	The local node has detected that the connection to the remote node has been made dormant by the remote node or the connection between the local and remote nodes has not been defined on the remote node.
dormant by mutual request	D-B	The local and remote nodes have both requested the connection be dormant by an operator issuing a TARGET DORMANT command on each system.
dormant in error	D-E	The local node is dormant and a failure is experienced while saving RRSF requests for later processing.
defined	DEF	 TARGET information has been defined, but no conversation occurs. This state occurs: Between member systems of a multisystem node. Systems in a multisystem node do not communicate with each other. Between a local nonmain system and a nonmain system on a remote multisystem node. Nonmain systems of multisystem nodes can communicate with single-system nodes and with the main systems of multisystem nodes, but they do not communicate with nonmain systems of other multisystem nodes.
not defined (initial)	???	No connection has been established to the node due to insufficient configuration information, or because a TARGET OPERATIVE or TARGET DORMANT command has not been issued for the node.

These connection states describe the state of the local node as well as the state of a connection between the local node and a remote node.

For example, from the local node perspective, operative active (O-A) means that the local node is now an APPC server and is able to accept connections to remote nodes. Dormant by local request (D-L) means that it is no longer an APPC server (or never was an APPC server) and no NEW conversations are accepted (existing O-A conversations are unaffected).

These connection states also describe the state of the local node when you have no remote node connection because you haven't specified PROTOCOL information. The local node can be operative active (O-A), but will NOT be an APPC server. The local node can be dormant by local request (D-L), but not dormant by remote request (D-R) or dormant by mutual request (D-B). If VSAM errors occur, the local node can be either operative in error (O-E) or dormant in error (D-E).

Connection state changes after a successful TARGET command

The following table shows the connection state as seen on the local node after a successful TARGET command is issued on the local node to change the connection state between the local and remote nodes.

For example, if the connection state as seen on the local node is operative in error (O-E) and the local node issues a successful TARGET DORMANT command, the connection state, as seen by the local node, would be dormant by local request (D-L).

Table 22 Table of	Now Connoction	Status Rasad on	a Successful TARGI	T Command
Table 22. Table UI	NEW CONTROLION	States Daseu Uli d	1 JUULESSIUI IANGI	- I CUIIIIIIaiiu

Previous Connection State	After a successful TARGET OPERATIVE command	After a successful TARGET DORMANT command	After a successful TARGET DELETE command
O–A	O-P-C	D–L	error message received
O-P-C	O-P-C	D–L	error message received
O-P-V	O-P-C	D–L	error message received
O-E	O-P-C	D-L	error message received
D–L	O-P-C	D–L	connection deleted
D-R	O-P-C	D–B	error message received
D–B	O-P-C	D–B	connection deleted
D–E	O-P-C if INMSG and OUTMSG workspace data sets can be opened, else D-E	D-L if INMSG and OUTMSG workspace data sets can be opened, else D-E	connection deleted
DEF	DEF Message IRRM035I is issued to syslog.	DEF Message IRRM035I is issued to syslog.	connection deleted

Actions to recover from an RRSF failure

RRSF can experience the following types of failures:

1. An ABEND that causes ESTAE processing. For detailed information, see RRSF ESTAE processing.

Recovery actions

- 2. An error return code from an MVS system service. For detailed information, see Failure of MVS System Service.
- 3. An error return code from APPC/MVS. For detailed information, see APPC return code handling.
- 4. An error return code from a request to VSAM. For detailed information, see VSAM failures.

RRSF ESTAE processing

ESTAE or ESTAI processing occurs when MVS detects an abnormal end during processing of a task within the RACF subsystem address space.

The actions indicated here are normally done internally by RACF itself. However, in some cases, a manual RESTART command might be necessary.

The following is done during recovery processing:

- 1. If the task that failed had not abended during recovery processing:
 - a. If the task is initializing:
 - 1) The task terminates to clean up its resources.
 - 2) Another attempt is made to re-create the task.
 - b. If the task is processing an item:
 - 1) The queue of waiting work is preserved.
 - 2) The current task is marked as being in recovery processing.
 - 3) In-use resources for the current item are freed.
 - 4) The current item is restarted.
 - c. If the task is terminating, termination continues and the abend is ignored.
 - d. If the task that failed is in recovery processing:
 - 1) Resources in use for the task are released.
 - 2) If the failure occurs when processing the same item for the second time. the item is deleted and output to be returned to the originator is created.
 - 3) The task that has failed is restarted.

Failure of MVS System Service

When an error return code from an MVS system service is detected, an attempt is made to recover the work being done by RRSF. The basic retry scheme depends on where the error is detected. Most of the tasks within RRSF have the following structure:

- 1. An initialization section
- 2. A processing loop
- 3. A termination section

If errors are detected in the initialization section, the error is recorded and the task is restarted.

Note: The RACF subsystem address space currently attempts to restart a task five times before an abend is issued.

The actions indicated here are normally done internally by RRSF itself. However, in some cases, a manual RESTART command might be necessary.

If errors are detected within the processing loop, the following steps are done:

- 1. An entry is created in the LOGREC data set at the time of failure.
- 2. The element is retried.
- 3. If retry fails,
 - a. Another entry is created in the LOGREC data set.
 - b. The failing item is discarded.
 - c. If possible, returned output is sent to the originator.
 - d. The task is restarted.

If errors are detected in the termination section, the error is recorded and termination continues. The termination code is usually entered when the task in the RACF subsystem address space is being restarted or stopped.

APPC errors

APPC is the communications vehicle for sending and receiving messages from one RRSF node to another. This discusses:

- · Initializing connection errors
- APPC return code handling
- · APPC and the RACF RESTART command
- VSAM failures

Initializing of connections

There is a class of problems that occur because of the order that the MVS address spaces become activated during a system IPL. As an MVS system is being IPLed, address spaces reach a state in which they are able to service requests at different rates. Therefore, there is no assurance that the VTAM and APPC address spaces, that are necessary to service RRSF requests, are available when the RACF subsystem address space issues its first request.

Attempting to activate the connections or send information to remote nodes when the RACF subsystem address space is started, but before VTAM and APPC have completed initialization, result in APPC failures. Normally, such APPC failures cause the connections between the two nodes to become operative in error when the first attempt is made. Instead, RRSF allows the RACF subsystem address space to continue to poll for APPC/MVS availability and when available, attempts to register the RACF subsystem address space as an APPC/MVS server.

If the RRSF APPC server fails to successfully register with APPC/MVS, error message IRRC023I is issued to the MVS operator console and RRSF initialization discontinues.

A registration attempt to APPC/MVS also occurs if:

- A local node is in a dormant state,
- A TARGET command is issued to make the connection operative, and
- Protocol information has been supplied.

A subsequent TARGET LIST command against the node would show a connection state of operative active.

Note: If MODENAME is not specified in the TARGET command, RACF sends a default name to APPC that allows the connection to complete successfully. This default name, IRRMODE, is placed in IRRNODE. However, since there was no explicit specification by the user and the default name is a RACF internal, the TARGET LIST output shows "NOT SPECIFIED".

APPC return code handling

The actions indicated here are normally done internally by RRSF itself. However, in some cases, a manual RESTART command might be necessary.

The MVS callable system services, that are used to implement the APPC or LU6.2 protocols, provide return codes to report the status of the request. Normally, a failure causes:

- The connection to be marked as operative in error
- · A symptom record to be created in the LOGREC data set. See Creation of LOGREC data set entries for details.

However, if RACF receives one of the following three error conditions back from APPC, RACF retries the error:

- Allocate_failure_retry
- TP not available retry
- Resource failure retry

If after 10 times, RACF still receives an error return code, it is considered a non-retryable error and:

- The connection is marked as operative in error.
- A symptom record is created in the LOGREC data set. See Creation of LOGREC data set entries for details.

APPC missing interrupts: Another type of APPC error occurs when the MVS callable system service that attempts to perform an APPC function never completes. One way this can occur is if the partner remote RACF subsystem address space starts the TP program, but doesn't complete the request. A missing interrupt handler (MIH) uses a timer to wait for the transaction to complete. When the timer expires, the MIH breaks the connection and declares an error. The connection between the two nodes is marked as operative in error and message IRRC022I is issued.

APPC and the RACF RESTART command

The RESTART command provides a way to recycle or recover a hung or stopped task. See z/OS Security Server RACF Command Language Reference for the syntax of the RESTART command.

The preferred way to recycle a connection is not to use the RESTART command. Instead, the operator should use the TARGET command to make the connection to the node dormant and then operative. This method fails if the task is hung waiting for outstanding work. Use the RESTART command to recycle a connection only after an unsuccessful attempt at using the TARGET command to make that connection dormant and then operative.

On restart, the partner node always marks the sender as operative in error. The node being restarted then attempts to handshake with the partner to restore the connection.

Deleted node: A command can be executing in the RACF subsystem address space and the node definition for the node on which the command originated can be removed. While requiring the connection to the node to be dormant before it can be deleted reduces the probability of this occurring, it is still possible.

If a message is targeted to a node that is no longer defined to RRSF, the following actions are done:

· A symptom record is created.

· The command output or the command is discarded.

VSAM failures

The checkpoint information is stored in a VSAM key-sequenced data set (KSDS). These files can be unusable for a number of operational reasons, such as:

- There are I/O errors on the device that contains the VSAM data set.
- The operator has made the device inactive or unavailable.
- There is insufficient space to store the next record.

The actions indicated here are normally done internally by RRSF itself. However, in some cases, a manual RESTART command might be necessary.

If VSAM errors occur on the INMSG or OUTMSG data set, that prevent the records from being written to or deleted from the data sets, RRSF does the following:

- · Shuts down the connection by:
 - Rejecting all INBOUND APPC transactions by marking all affected successfully established connections as operative in error
 - Marking all dormant connections as dormant in error
 - Rejecting all directed commands that would require the use of the damaged VSAM data set
- · Notifies the appropriate people by:
 - Writing a message to the system console
 - Creating a symptom record in the LOGREC data set
- Allows for correction by:
 - Attempting to close and de-allocate the VSAM data set that is experiencing errors

An error message is issued to the MVS operator console when a VSAM data set experiences an error. Some common error messages are IRRC029I and IRRC030I, which indicate problems in trying to write to the workspace data sets, and IRRC031I, which indicates that a workspace data set is full. Associated messages IRRC032I and IRRC033I are also issued, indicating that the specified connection has received a DORMANT ERROR or OPERATIVE ERROR.

After the error has been corrected, the following commands must be processed to reactivate the connection:

```
TARGET NODE (nodename) DORMANT
TARGET NODE(nodename) WORKSPACE([current or new settings])
TARGET NODE(nodename) OPERATIVE
```

Note: RACF profiles are recommended to protect the INMSG and OUTMSG data sets.

Automatic direction and VSAM errors: Automatic direction should be transparent to most persons who issue RACF commands, change their passwords, or take actions that result in application updates. They are usually not aware that their actions have caused an RRSF request to be automatically directed. Therefore, VSAM errors are not reported to the issuer of the request. Instead, the users who are specified on the NOTIFY and OUTPUT keywords of the RACF SET command (which might include the command issuer via &RACUID) receive an error message that the RRSF request was not sent to the appropriate remote node because of a VSAM file failure.

Recovery actions

Why are VSAM failures treated differently than APPC failures or even failures within the RACF subsystem address space? VSAM failures are special and critical because the request and the returned output are checkpointed in the VSAM files. If the VSAM files are unusable, there is no record of the RACF request or the output.

When an RRSF request generated by automatic direction is processed and it experiences a hard VSAM failure (that is, it cannot be written to the file and has not already been saved somewhere else) the standard failure output is sent to the users who are specified on the NOTIFY and OUTPUT keywords of the RACF SET command. This hard VSAM failure can only occur on the node where the request originated and before it is stored in the OUTMSG data set for the target node. In all other cases of a VSAM failure, a copy of the request or output exists in another VSAM file.

Password synchronization and VSAM failures: If possible, VSAM failures for password synchronization requests are processed the same as a VSAM failure for a directed command. A password synchronization failure generates RRSFLIST output and an error message to the TSO user.

IRRBRW00 utility and VSAM data sets: If you have a DASD problem or have a need for off-line diagnosis of the RRSF VSAM data sets, RACF has an APF-authorized utility called IRRBRW00 that allows you to dump the RACF data contained within the VSAM data sets. Because this utility provides the capability to dump sensitive RACF data such as RACF command text and returned output, be careful to control access to this utility.

In order to prevent inadvertent disclosure of the data in the VSAM data sets, RACF requires that a user have read access to the resource name IRRBRW00 in the RRSFDATA class in order to run the IRRBRW00 utility. If the class is not active or no profile is defined, the user is denied access to run the utility. The user also needs RACF access to the VSAM data set to be dumped. VSAM data sets can be protected via normal data set protection using profiles that protect the data set names:

- prefix.sysname_or_wdsqual.INMSG
- prefix.sysname or wdsqual.OUTMSG
- prefix.local_luname.remote_luname_or_wdsqual.INMSG
- prefix.local_luname.remote_luname_or_wdsqual.OUTMSG

To ensure the integrity of the data in these files, it is recommended that you set up these profiles and limit the access to only those with a need to know. You can use the RACF TARGET command to determine the VSAM data set names being used by the RACF remote sharing facility.

The IRRBRW00 utility is provided for diagnostic purposes only. For complete instructions on running IRRBRW00, see the RACJCL member of SYS1.SAMPLIB and read the IRRBRW00 sample.

Recording of errors

Environmental errors and transmission errors need to be reported to allow for their correction. When the RACF subsystem address space is unable to access a requested system resource, it records this type of error. Further, the RACF subsystem address space attempts to notify the originator of the command that it was unsuccessful. It might also need to stop transmitting to the affected node. The following mechanisms are used:

- · A symptom record is created on the system experiencing the failure and stored in the LOGREC data set.
- If possible, an error message reporting the failure is sent back in the RRSFLIST data set (standard returned output) when the failure is not in RRSF. If the failure is in RRSF, then only a symptom record is created. This returned output is an error message. If the failing request is in storage, the failing request is added to the output. To the system where the request originated, the returned output is identical to the output returned when a command has successfully processed.
- RRSF attempts to retry the error after creating the appropriate record of the failure.

APPC failures that reflect either transmission errors or definition errors do not cause an abend. Instead they cause the connection between the two nodes to be marked as operative in error. This prevents attempts to send commands until either the operator fixes the problem or the remote node activates the connection.

Creation of LOGREC data set entries

When the RACF subsystem address space requests an MVS system resource or uses an MVS system service and is unsuccessful, this failure is recorded. If the failure is not recorded by MVS, RACF puts the symptom records in the LOGREC data set.

z/OS MVS Programming: Assembler Services Guide categorizes information contained within the symptom records as:

- Component Data This identifies the application in which the error occurred (that is, RACF subsystem address space).
- Primary SDB symptoms This contains the primary string of problem symptoms. This data is used for duplicate problem recognition (See Table 23).
- Secondary SDB symptoms This contains any additional diagnostic values saved at the time of the error.
- Variable Data This contains diagnostic data, such as portions of data areas or parameter lists pertinent to the error.

Table 23 shows the contents of the primary symptom string that the symptom record contains.

Table 23. Contents of Primary Symptom String for a RACF Subsystem Address Space Error

SDB Key Literal	Usage
RIDS/	Module CSECT name
RIDS/	Load module name
PCSS/	System service (MVS or RACF macro) that failed
PRCS/	Return code from service
PRCS/	Reason code from service (if no reason code is available, this field contains a value of zero)

Table 24 shows the contents of the secondary symptom string that the symptom record contains.

Recovery actions

Table 24. Contents of Secondary Symptom String for a RACF Subsystem Address Space

SDB Key Literal	Usage
ADRS/	Offset of service that failed

Table 25 shows the contents of the variable symptom string that the symptom record contains.

Table 25. Potential Contents of Variable Symptom String for a RACF Subsystem Address Space Error

Field	Description
LUNAME	APPC partner LUNAME
TPNAME	APPC partner TPNAME
MODENAME	APPC partner MODE NAME
MISC STRING	Additional information for some service failures

Table 26 shows the additional information that the symptom record contains.

Table 26. Additional LOGREC Data for a RACF Subsystem Address Space Error

Field	Value
COMPDSC	RACF subsystem address space
PROBLEM	Name of failing service
SERVLEV	Service level of module
COMPID	Component ID (5752XXH00)
COMPLEV	Component level (260)

Chapter 6. Diagnosis reference for RACF

This topic contains:

- Parameter list descriptions (see Parameter list descriptions)
- Process flows (see Process flows for RACF)

Parameter list descriptions

This describes parameter lists passed to RACF when a RACF macro is invoked. Installation exits, which are described in *z/OS Security Server RACF System Programmer's Guide*, also use parameter lists, which are described in *z/OS Security Server RACF Data Areas*. See Appendix A, "The Inventory Control Block (ICB)" for information on the ICB (inventory control block).

The parameter lists used by RACF in processing RACF commands and the RACF report writer are standard TSO/E parameter lists. See *z/OS TSO/E Customization* for information on these parameter lists.

The parameter lists used by RACF in processing RACF utilities and DSMON are standard MVS parameter lists.

Table 27 is a quick reference that identifies the system macro-request types that are replacements for the independent RACF system macros. For more information on both types, see *z/OS Security Server RACROUTE Macro Reference*.

Table 27. Cross-Reference for RACROUTE REQUEST=type, the Independent RACF System Macros, and the Parameter List Name

,		
RACROUTE REQUEST=type	Independent RACF System Macro	Parameter List
REQUEST=AUDIT	None	AUDIT
REQUEST=AUTH	RACHECK	AUTH
REQUEST=DEFINE	RACDEF	DEFINE
REQUEST=DIRAUTH	None	DIRAUTH
REQUEST=EXTRACT	RACXTRT	EXTRACT
REQUEST=FASTAUTH	FRACHECK	FASTAUTH
REQUEST=LIST	RACLIST	LIST
REQUEST=SIGNON	None	SIGNON
REQUEST=STAT	RACSTAT	STAT
REQUEST=TOKENBLD	None	TOKENBLD
REQUEST=TOKENMAP	None	TOKENMAP
REQUEST=TOKENXTR	None	TOKENXTR
REQUEST=VERIFY	RACINIT	VERIFY
REQUEST=VERIFYX	None	VERIFYX

The following are the parameter lists:

- RACROUTE parameter list
- · AUDIT service parameter list
- AUTH service parameter list
- · DEFINE service parameter list
- DIRAUTH Service Parameter List


© Copyright IBM Corp. 1994, 2008

Parameter descriptions

- EXTRACT service parameter list
- FASTAUTH service parameter list
- · LIST service parameter list
- SIGNON service parameter list
- STAT service parameter list
- TOKENBLD service parameter list
- TOKENMAP/TOKENXTR service parameter list
- VERIFY/VERIFYX service parameter list
- ICHEINTY parameter list

Checking the parameter list passed to RACF goes into detail to show you how to locate parameters in a dump. To do this, you find the contents of register 1.

If register 1 is zero, then the RACROUTE macro was issued, and module ICHRFR00 issued the RACF macro. In this case, register zero points to a two-word parameter list. The first word of this parameter list points to the RACF SVC parameter list, and the second word of this parameter list points to the SAF parameter list. This is shown in the following:



If register 1 is not zero, then this is the address of the parameter list passed with the macro request.

RACROUTE parameter list

The RACROUTE parameter list is also called the SAF router parameter list or the MVS router parameter list. It is mapped by macro ICHSAFP. For another description of this parameter list that includes field names, see z/OS Security Server RACF Data Areas.




Figure 25. RACROUTE Parameter List (Part 1 of 2)

Parameter descriptions

These areas show up on both MVS and VM systems, but they are used only on VM.




Figure 25. RACROUTE Parameter List (Part 2 of 2)

AUDIT service parameter list






Figure 26. AUDIT Service Parameter List

AUTH service parameter list



¹ This field is zero if bit 4 of the flag byte at offset 4 is one (input was RACROUTE REQUEST=AUTH).

Figure 27. AUTH Service Parameter List (Part 1 of 4)




¹ This field is zero if bit 4 of the flag byte at offset 4 is one (input was RACROUTE REQUEST=AUTH).

Figure 27. AUTH Service Parameter List (Part 2 of 4)

² This field is zero if bit 4 of the flag byte at offset 4 is zero (input was RACHECK macro).

AUTH parameters



¹ This field is zero if bit 4 of the flag byte at offset 4 is one (input was RACROUTE REQUEST=AUTH). ² This field is zero if bit 4 of the flag byte at offset 4 is zero (input was RACHECK macro).

Figure 27. AUTH Service Parameter List (Part 3 of 4)





Figure 27. AUTH Service Parameter List (Part 4 of 4)

DEFINE service parameter list



¹ This field is zero if bit 4 of the flag byte at offset 4 is one (input was RACROUTE REQUEST=DEFINE).

Figure 28. DEFINE Service Parameter List (Part 1 of 6)




Figure 28. DEFINE Service Parameter List (Part 2 of 6)

DEFINE parameters





Figure 28. DEFINE Service Parameter List (Part 3 of 6)



² This field is zero if bit 4 of the flag byte at offset 4 is zero (input was RACDEF macro).

Figure 28. DEFINE Service Parameter List (Part 4 of 6)

DEFINE parameters




Figure 28. DEFINE Service Parameter List (Part 5 of 6)




Figure 28. DEFINE Service Parameter List (Part 6 of 6)

DIRAUTH Service Parameter List




Figure 29. DIRAUTH service parameter list

EXTRACT service parameter list




Figure 30. EXTRACT Service Parameter List (Part 1 of 3)

(The following is used when TYPE = ENVRXTR.)





Figure 30. EXTRACT Service Parameter List (Part 2 of 3)

EXTRACT parameters

(The following is used when TYPE=ENCRYPT.)



(The following is used when TYPE is not ENCRYPT or ENVRXTR.)




Figure 30. EXTRACT Service Parameter List (Part 3 of 3)

FASTAUTH service parameter list




Figure 31. FASTAUTH Service Parameter List

LIST service parameter list




Figure 32. LIST Service Parameter List

SIGNON service parameter list




Figure 33. SIGNON Service Parameter List

STAT parameters

STAT service parameter list




Figure 34. STAT Service Parameter List

TOKENBLD service parameter list




Figure 35. TOKENBLD Service Parameter List (Part 1 of 4)

TOKENBLD parameters




Figure 35. TOKENBLD Service Parameter List (Part 2 of 4)

TOKENBLD parameters




Figure 35. TOKENBLD Service Parameter List (Part 3 of 4)

TOKENBLD parameters




Figure 35. TOKENBLD Service Parameter List (Part 4 of 4)

TOKENMAP/TOKENXTR service parameter list




Figure 36. TOKENMAP/TOKENXTR Service Parameter List

VERIFY/VERIFYX service parameter list




Figure 37. VERIFY/VERIFYX Service Parameter List (Part 1 of 4)

VERIFY/VERIFYX parameters




Figure 37. VERIFY/VERIFYX Service Parameter List (Part 2 of 4)

VERIFY/VERIFYX parameters




Figure 37. VERIFY/VERIFYX Service Parameter List (Part 3 of 4)




Figure 37. VERIFY/VERIFYX Service Parameter List (Part 4 of 4)

ICHEINTY parameter list





Figure 38. ICHEINTY Parameter List (Part 1 of 3)



¹ This field has a value only when the byte at +3 (entry type) has a value of X'05'.

Figure 38. ICHEINTY Parameter List (Part 2 of 3)

ICHEINTY parameters




Figure 38. ICHEINTY Parameter List (Part 3 of 3)

Process flows for RACF

This provide process flows for:

- Commands
- Directed commands
- Macros
- · Installation exits
- Utilities
- · The report writer
- · The SMF data unload utility
- · Callable services

Process flow for RACF commands




Figure 39. Process Flow for RACF Commands

Process flow for RACF directed commands




Figure 40. Process Flow for RACF Directed Commands

Process flow for RACF macros




Figure 41. Process Flow for RACF Macros

Process flow for RACF installation exits




Figure 42. Process Flow for RACF Installation Exits (Part 1 of 2)




Figure 42. Process Flow for RACF Installation Exits (Part 2 of 2)

Process flow for RACF utilities




Figure 43. Process Flow for RACF Cross-Reference and Database Unload Utilities




Figure 44. Process Flow for RACF Remove ID Utility




Figure 45. Process Flow for Other RACF Utilities

Process flow for the RACF Report Writer




Figure 46. Process Flow for RACF Report Writer

Process flow for SMF Data Unload Utility (IRRADU00)




Figure 47. Process Flow for SMF Data Unload Utility. The USER2 exit is invoked once for each record that meets the criteria in the IFASMFDP control statements. See z/OS MVS System Management Facilities (SMF) for more information. The USER3 exit is invoked once.

Process flow for RACF Callable Services




Figure 48. Process Flow for RACF Callable Services

Error recording for Callable Services

Environmental errors must be reported to allow their correction. Some of the RACF callable services create symptom records for errors and store them in the LOGREC data set.

 $z/OS\ MVS\ Programming:$ Assembler Services Guide categorizes information contained in the symptom records as:

· Component data

Error recording

This identifies the application in which the error occurred (that is, the RACF subsystem address space).

· Primary SDB symptoms

This contains the primary string of problem symptoms. This data is used for duplicate problem recognition (see Table 28).

Secondary SDB symptoms

This contains any additional diagnostic values saved at the time of the error. See Table 29.

· Variable data

This contains diagnostic data, such as portions of data areas or parameter lists pertinent to the error. See Table 30.

Table 28 shows the contents of the primary symptom string in the symptom record.

Table 28. Contents of Primary Symptom String for a Callable Service Error

SDB Key Literal	Usage
RIDS/	Module CSECT name
RIDS/	Load module name (IRRRFR10)
PCSS/	System service (MVS or RACF macro) that failed
PRCS/	Return code from service
PRCS/	Reason code from service (if no reason code is available, this field contains a value of zero)

Table 29 shows the contents of the secondary symptom string.

Table 29. Contents of Secondary Symptom String for a Callable Service Error

SDB Key Literal	Usage
ADRS/	Offset of service that failed

Table 30 shows the additional information that the symptom record contains.

Table 30. Additional LOGREC Data for a Callable Service Error

Field	Value
COMPDSC	RACF callable service
PROBLEM	Name of failing service
SERVLEV	Service level of module
COMPID	Component ID (5752XXH00)
COMPLEV	Component level (260)

Variable data recorded by RACF Callable Services

Each RACF callable service records additional variable data specific to the problem:

R_usermap (CSECT IRRRIM00)

- · Error determining the RACF user ID associated with an application user identity
 - Service name: RACXTRT or ICHEINTY

- Variable data: The string 'IRRRIM00_XXXX:', where XXXX is the procedure name from which error occurs
- Additional variable data: application user identity and field names, such as SNAME or UNAME
- · Error determining the application user identity associated with a RACF user
 - Service name: RACXTRT
 - Variable data: The string 'IRRRIM00_XXXX:', where XXXX is the procedure name from which error occurs
 - Additional variable data: RACF user ID and field names, such as SNAME or UNAME
- · Figure 49 shows an example of a symptom record when the user name is not found in an alias index entry but is found in the mapping profile.

Error recording

	PTOM RECORD	REPORT:	REPORT DAT	E: 03	32 00	DAY YEAR		
SCP: VS		DEL: 438	ERROR DATE 1 685	: (HH	932 00 MM SS.	ГН		
SEARCH ARG	SE UMENT ABSTRACT PIDS/5752XXHG RIDS/IRRRFR1G	: 00 PRCS/00						
	CPU MODEL: 43 CPU SERIAL: 12 SYSTEM: RA RELEASE LEVEL SYSTEM DATA AT COMPONENT DATA	27685 ACFR10 OF SERVIC ARCHITEC AAT ARCHI	E ROUTINE: TURE LEVEL: TECTURE LEV	TIM BCF F 1 EL: 1	10 10	3:48.85		
	SYSTEM DATA: INFORMATION: COMPONENT IE COMPONENT RE SERVICE RELE DESCRIPTION PROBLEM ID:): ELEASE LEV EASE LEVEL OF FUNCTI	5752XX EL: 7703	H00 3 /OS UN	NIX SYSTEM	•	SERV.	
PRIMARY SY	MPTOM STRING: PIDS/5752XXH RIDS/IRRRFR1		000000C PRC	S/0006	90000 RIDS	S/IRRRIM00		
	SYMPTOM		YMPTOM DATA		EXPLANATI(ON		
PIDS/5752XXH00 PRCS/0000000C PRCS/00000000 RIDS/IRRRIM00 RIDS/IRRFR10#L			752XXH00 0000000C 0000000 RRRIM00 RRRFR10#L	(F	COMPONENT IDENTIFIER RETURN CODE RETURN CODE ROUTINE IDENTIFIER ROUTINE IDENTIFIER			
SECONDARY	SYMPTOM STRING ADRS/00001400							
	SYMPTOM		PTOM DATA		LANATION			
	ADRS/00001400					ESS		
KEY = F000 +000 C9D +010 968 +020 A38 +030 LENGT	9D9D9 C9D4F6 37A40 E2D5C1 5A240 C99586 H(0048) ==> AL 404040	000100 (0 0F0 6DC1 D4 C540 696 4040	064) 9389 81A2 D4E8 40D3 4040 4040	6DD3 D596 4040	OC:	RRIMOO_ALIA : SNAME MY S INFO		
	31800 000000 27685 438100		032F 0828	4885	<c.< td=""><td>E.A</td><td>E</td></c.<>	E.A	E	
Figure 10	An Evample of	a Sympton	Record wh	on an	SNAME	s not found	in the	

Figure 49. An Example of a Symptom Record when an SNAME is not found in the alias index entry but is found in the mapping profile (Part 1 of 2)

SYMP	ΓΟΜ RECORD				
+000	E2D9F4F3	F8F1F1F2	F7F6F8F5	FFFFBCF1	SR43811276851
+010	B388C6D9	4BC38185	40404040	40404040	.HFR.CAE
+020	4040D9C1	C3C6D9F1	F040F5F7	F5F2C8C2	RACFR10 5752HB
+030	C2F7F7F0	F3400080	00000000	00000000	B7703
+040	F1F00030	00640070	00490138	000E0181	10A
+050	0068018F	00000000	00000000	00000000	
+060	00000000	00000000	00000000	00000000	
+070	E2D9F2F1	F1F0F5F7	F5F2E7E7	C8F0F000	SR21105752XXH00.
+080	F7F7F0F3	C8D9C6F7	F7F0F340	00000000	7703HRF7703
+090	00000000	00000000	00000000	D9C1C3C6	RACF
+0A0	40D69785	95C58489	A3899695	40C38193	z/OS UNIX SYSTEM
+0B0	93818293	8540E285	99A54B40	00000000	CALLABLE SERV
+0C0	00000000	C9C3C8C5	C9D5E3E8	00000000	ICHEINTY
+0D0	00000000	066839B1	066839B1	066839BF	
+0E0	066839BF	06683A27	06683A27	01000000	
+0F0	06683830	00000000	00000000	F0F1F2F3	0123
+100	F4F5F6F7	F8F9C1C2	C3C4C5C6	0049000E	456789ABCDEF
+110	0068000F	00000000	F0F0F0F0	F1F4F0C3	0000140C
+120	00000000	00000000	00000000	00000000	
+130	00000000	00000000	D7C9C4E2	61F5F7F5	PIDS/575
+140	F2E7E7C8	F0F040D7	D9C3E261	F0F0F0F0	2XXH00 PRCS/0000
+150	F0F0F0C3	40D7D9C3	E261F0F0	F0F0F0F0	000C PRCS/000000
+160	F0F040D9	C9C4E261	C9D9D9D9	C9D4F0F0	00 RIDS/IRRRIM00
+170	40D9C9C4	E261C9D9	D9D9C6D9	F1F07BD3	RIDS/IRRRFR10#L
+180	40C1C4D9	E261F0F0	F0F0F1F4	F0C340F0	ADRS/0000140C 0
+190	000064C9	D9D9D9C9	D4F0F06D	C1938981	IRRRIM00_ALIA
+1A0	A26DD396	837A40E2	D5C1D4C5	40D4E840	S_LOC: SNAME MY
+1B0	D3D596A3	85A240C9	95869640	40404040	LNOTES INFO
+1C0	LENGTH(0048)	==>ALL BY	TES CONTAIN	X'40'.	

Figure 49. An Example of a Symptom Record when an SNAME is not found in the alias index entry but is found in the mapping profile (Part 2 of 2)

getGMAP (CSECT IRRRGM01)

- · Error extracting the group name corresponding to the input group ID
 - Service name: RACXTRT or ICHEINTY
 - Variable data: The string 'IRRRGM01 XXXX: YYYY', where XXXX is the procedure name from which error occurs and YYYY is the GROUP mapping profile name for RACXTRT service or is the GROUP Alias name for ICHEINTY service
- Error extracting the group ID corresponding to the input group name
 - Service name: RACXTRT
 - Variable data: The string 'IRRRGM01 XXXX: YYYY', where XXXX is the procedure name from which error occurs and YYYY is the GROUP profile name

getUMAP (CSECT IRRRUM01)

- · Error extracting the user name corresponding to the input user ID
 - Service name: RACXTRT or ICHEINTY
 - Variable data: The string 'IRRRUM01_XXXX: YYYY', where XXXX is the procedure name from which error occurs and YYYY is the USER mapping profile name for RACXTRT service or is the USER application identity name for ICHEINTY service
- Error extracting the user ID corresponding to the input user name
 - Service name: RACXTRT
 - Variable data: The string 'IRRRUM01 XXXX: YYYY', where XXXX is the procedure name from which the error occurs and YYYY is the USER profile name

Error recording

 Figure 50 shows an example of a symptom record when the user name is not found in an alias index entry but is found in the mapping profile.

```
TYPE: SYMPTOM RECORD
                            REPORT: SOFTWARE EDIT REPORT
                                                                 DAY YEAR
                                     REPORT DATE: 032 00
SCP:
      VS 2 REL 3
                                     ERROR DATE: 032 00
                   MODEL: 4381
                                              HH MM SS.TH
                   SERIAL: 127685 TIME: 09:16:23.25
SEARCH ARGUMENT ABSTRACT:
         PIDS/5752XXH00 PRCS/0000000C PRCS/00000000 RIDS/IRRRUM01
         RIDS/IRRRFR10#L
SYSTEM ENVIRONMENT:
                                        DATE: 032 00
         CPU MODEL: 4381
         CPU SERIAL: 127685
                                        TIME: 09:16:23.25
         SYSTEM: RACFR10
                                                MVS
         RELEASE LEVEL OF SERVICE ROUTINE:
                                                HBB7703
         SYSTEM DATA AT ARCHITECTURE LEVEL:
                                                10
         COMPONENT DATA AT ARCHITECTURE LEVEL: 10
         SYSTEM DATA: 00000000 00000000
                                                |.....
COMPONENT INFORMATION:
          COMPONENT ID:
                                   5752XXH00
          COMPONENT RELEASE LEVEL: 7703
          SERVICE RELEASE LEVEL:
                                    HRF7703
          DESCRIPTION OF FUNCTION: RACF z/OS UNIX SYSTEM CALLABLE SERV.
          PROBLEM ID:
                                    ICHEINTY
PRIMARY SYMPTOM STRING:
          PIDS/5752XXH00 PRCS/0000000C PRCS/00000000 RIDS/IRRRUM01
          RIDS/IRRRFR10#L
          SYMPTOM
                               SYMPTOM DATA EXPLANATION
                               -----
                         5752XXH00 COMPONENT IDENTIFIER
0000000C RETURN CODE
00000000 RETURN CODE
IRRRUM01 ROUTINE IDENTIFIER
IRRRFR10#L ROUTINE IDENTIFIER
          PIDS/5752XXH00
          PRCS/0000000C
          PRCS/00000000
          RIDS/IRRRUM01
          RIDS/IRRRFR10#L
SECONDARY SYMPTOM STRING:
          ADRS/00000BAA
          SYMPTOM
                               SYMPTOM DATA
                                               EXPLANATION
           _____
                               -----
                                                _____
          ADRS/00000BAA
                               00000BAA
                                                STORAGE ADDRESS
FREE FORMAT COMPONENT INFORMATION:
KEY = F000 LENGTH = 000100 (0064)
+000
       C9D9D9D9 E4D4F0F1
                               6DC1D3C9
                                           C1E26DE4
                                                        |IRRRUM01 ALIAS U|
                 40F1F2F3
                             F4F5F6F7
                                                       LOC: 12345678
+010
       D3D6C37A
                                          F8404040
+020 LENGTH(0064) ==> ALL BYTES CONTAIN X'40'.
       40404040
+060
HEX DUMP OF RECORD:
HFADFR
                   00000000
                               0000032F
                                                        <C.....
+000
       4C831800
                                           09162325
+010
       FF127685
                   43810000
                                                        ...E.A..
```

Figure 50. An Example of a Symptom Record when a UID is not found in the alias index entry but is found in the mapping profile (Part 1 of 2)

SYMPT	OM RECORD				
+000	E2D9F4F3	F8F1F1F2	F7F6F8F5	FFFFBCF1	SR43811276851
+010	B388D17B	767DA544	40404040	40404040	.HJ#.'V.
+020	4040D9C1	C3C6D9F1	F040F5F7	F5F2C8C2	RACFR10 5752HB
+030	C2F7F7F0	F3400080	00000000	00000000	B7703
+040	F1F00030	00640070	00490138	000E0181	10A
+050	0068018F	00000000	00000000	00000000	
+060	00000000	00000000	00000000	00000000	
+070	E2D9F2F1	F1F0F5F7	F5F2E7E7	C8F0F000	SR21105752XXH00.
+080	F7F7F0F3	C8D9C6F7	F7F0F340	00000000	7703HRF7703
+090	00000000	00000000	00000000	D9C1C3C6	RACF
+0A0	40D69785	95C58489	A3899695	40C38193	z/OS UNIX SYSTEM
+0B0	93818293	8540E285	99A54B40	00000000	CALLABLE SERV
+0C0	00000000	C9C3C8C5	C9D5E3E8	00000000	ICHEINTY
+0D0	00000000	06694591	06694591	0669459F	JJ
+0E0	0669459F	06694607	06694607	01000000	
+0F0	06694410	00000000	00000000	F0F1F2F3	0123
+100	F4F5F6F7	F8F9C1C2	C3C4C5C6	0049000E	456789ABCDEF
+110	0068000F	00000000	F0F0F0F0	F0C2C1C1	00000BAA
+120	00000000	00000000	00000000	00000000	
+130	00000000	00000000	D7C9C4E2	61F5F7F5	PIDS/575
+140	F2E7E7C8	F0F040D7	D9C3E261	F0F0F0F0	2XXH00 PRCS/0000
+150	F0F0F0C3	40D7D9C3	E261F0F0	F0F0F0F0	000C PRCS/000000
+160	F0F040D9	C9C4E261	C9D9D9D9	E4D4F0F1	00 RIDS/IRRRUM01
+170	40D9C9C4	E261C9D9	D9D9C6D9	F1F07BD3	RIDS/IRRRFR10#L
+180	40C1C4D9	E261F0F0	F0F0F0C2	C1C140F0	ADRS/00000BAA 0
+190	000064C9	D9D9D9E4	D4F0F16D	C1D3C9C1	IRRRUM01_ALIA
+1A0	E26DE4D3	D6C37A40	F1F2F3F4	F5F6F7F8	S_ULOC: 12345678
+1B0	LENGTH(0064)	===> ALL BYT	ES CONTAIN X	('40'.	

Figure 50. An Example of a Symptom Record when a UID is not found in the alias index entry but is found in the mapping profile (Part 2 of 2)

InitACEE (CSECT IRRRIA00)

- Certificate decoding problem
 - Service name: DECX509B
 - Variable data: The following 6 fullwords:
 - 1. Address of the certificate passed to InitACEE
 - 2. Length of the certificate passed to InitACEE
 - 3. Address of the byte found to be in error
 - 4. Internal diagnostic word
 - 5. Number of certificate bytes recorded in the next 4 variable data sections
 - 6. Number of certificate bytes skipped at the beginning of the certificate when recording
 - Additional variable data: up to 1024 bytes of the certificate
- Error in certificate profile (user ID not valid)
 - Service name: GETUSERI
 - Variable data: The string 'Bad DIGTCERT Class Profile'
 - Additional variable data: The name of the DIGTCERT class profile found to be in error
- Error in certificate profile (user ID not defined to RACF)
 - Service name: BACINIT
 - Variable data: The string 'Bad DIGTCERT Class Profile'
 - Additional variable data: The name of the DIGTCERT class profile found to be in error
- Unexpected return code from R_cacheserv SAF callable service

- Service name: CACHSERV
- Variable Data: The 8 byte user ID input to R cachesery
- Primary symptom string return code: R_cacheserv return code
- Primary symptom string return code: R_cacheserv reason code
- Unexpected return code from RACROUTE REQUEST=VERIFY
 - Service name: RACINIT
 - Variable data: The nine character user id being verified (1 byte length followed by up to 8 characters for the user ID itself)

InitACEE (CSECT IRRRIA02)

- · Certificate decoding problem
 - Service name: DECX509B
 - Variable data: The following 6 fullwords:
 - 1. Address of the certificate passed to InitACEE
 - 2. Length of the certificate passed to InitACEE
 - 3. Address of the byte found to be in error
 - 4. Internal diagnostic word
 - 5. Amount of certificate data recorded
 - 6. Amount of certificate data truncated
 - Additional variable data: up to 1024 bytes of the certificate
- · Error retrieving the CERTAUTH certificate repeat group from the irrcerta profile.
 - Service name: RACXTRT
 - Variable data: The string 'Couldn't extract the CERTAUTH anchor USER profile, irrcerta'.
 - Additional variable data: none
- Error extracting the private key size (CERTPRVS) from a DIGTCERT profile.
 - Service name: RACXTRT
 - Variable data: The string 'Bad CERTAUTH class profile:'label-value
 - Additional variable data: The profile name

InitACEE (CSECT IRRRIA05)

- Error extracting the trust status (UACC) from a DIGTCERT profile
 - Service name: RACEXTR
 - Variable data: The string 'Bad DIGTCERT Class Profile'
 - Additional variable data: The profile name
- Error extracting date fields CERTSTRT, CERTEND from a DIGTCERT profile
 - Service name: RACEXTR
 - Variable data: The string 'Bad DIGTCERT Class Profile'
 - Additional variable data: The profile name
- Error extracting the CERTAUTH anchor in the USER profile.
 - Service name: RACEXTR
 - Variable data: The string 'Bad USER class profile irrcerta'

R cachesery (CSECT IRRRCH12)

- · Physical error accessing the CACHECLS profile on the RACF database
 - Service name: ICHEINTY

- Variable data: The string "LOCATE CACHECLS profile xxxx" where xxxx is the 16 byte profile name.
- Logical error with the contents of the CACHECLS profile read from the RACF database
 - Service name: Database (not a real Service, rather an indicator something was wrong with the profile read from the RACF database)
 - Variable data: The string "CACHECLS profile xxxx not valid:" where xxxx is the 16 byte profile name. Following that string is one of the following reasons the profile was determined not to be valid.
 - missing profile
 - profile not valid
 - timestamp is not correct
 - dataspace offset is not correct
 - dataspace size is not correct
 - dataspace count is not correct
 - cache version is not correct

R_cacheserv (CSECT IRRRCH13)

- · Physical error accessing the CACHECLS profile on the RACF database
 - Service name: ICHEINTY
 - Variable data: The string "{LOCATE | ALTER | ADD} CACHECLS profile xxxx" where xxxx is the 16 byte profile name.

R_cacheserv (CSECT IRRRCH14)

- Physical error accessing the CACHECLS profile on the RACF database
 - Service name: ICHEINTY
 - Variable data: The string "{NEXT | DELETE} CACHECLS profile xxxx" where xxxx is the 16 byte profile name.

R_cacheserv (all CSECTs IRRRCHQx in IRRRCH16)

- · Error occurred in dataspace layer
 - Service name: DISPLAYER
 - Variable data: xxxxxxxx yyyyyyyy zzzzzzzz aaaaaaaa bbbbbbbb: ccccccc
 - xxxxxxxx = Internal subroutine identifier
 - The following are possible values for xxxxxxxx. These identify the failing dataspace layer subroutine:

Table 31. Failing dataspace layer for an internal subroutine identifier

XXXXXXX	Dataspace layer call
8	dspCreate
24	dspDelete
28	dspConnect
32	dspExtend
36	dspExpose
40	dspHide
44	addAlet
48	delAlet
52	dspAdd
60	dspDisconnect

Table 31. Failing dataspace layer for an internal subroutine identifier (continued)

64	dasENQDS
68	dasDEQDs
76	dasSetVer
80	dasGetVer
84	dasCopyDS

- yyyyyyy = Failing system service The following are possible values for yyyyyyyy. These identify the failing system service or internal request:

Table 32. Failing system service for a failing system service identifier

ууууууу	Failing system service	
0	None	
4	TCBTOKEN	
8	DSPSERV CREATE	
12	ALESERV ADD	
16	DSPSERV DELETE	
20	Dataspace does not exist	
24	Dataspace header eyecatcher bad	
28	Irrrch10 not found	
32	IEANTCR	
36	IEANTRT	
40	IEANTDL	
44	DSPSERV EXTEND	
48	ALESERV DELETE	
Uppercase values are z/OS system macros. Lower case values are internal requests.		

- zzzzzzzz = failing system service return code
- aaaaaaaa = failing system service reason code
- bbbbbbbb = identifies R_cacheserv subroutine
- ccccccc = additional diagnostic text, such as "dspCreate failed"

R_cacheserv (CSECTs IRRRCHQx in IRRRCH16)

- · Error occurred in dataspace layer
 - Service name: DSPLAYER
 - Variable data: bbbbbbbb: ccccccc
 - bbbbbbbb = identifies R_cacheserv subroutine
 - ccccccc = additional diagnostic text

R_cacheserv (CSECTs IRRRCHQC in IRRRCH16)

- Recovery attempted after a failure during cache creation
 - Service name: REEXPOSE
 - Variable data: bbbbbbbb: RE-EXPOSE ccccccc dddddddd
 - bbbbbbbb = identifies R cacheserv subroutine
 - ccccccc = identifies failing object
 - dddddddd = successful or failed

R_cacheserv (CSECT IRRRCHQD, IRRRCHQG, IRRRCHQE in IRRRCH16)

- Name/token service failure
 - Service name: IEANTRT
 - Variable data: bbbbbbbb: IEANTRT error
 - bbbbbbbb = identifies R cacheserv subroutine

R_cacheserv (CSECT IRRRCHQG in IRRRCH16)

- · Name/token service failure
 - Service name: IEANTCR
 - Variable data: bbbbbbbb: IEANTCR Error
 - bbbbbbbb = identifies R_cacheserv subroutine

R_cacheserv (CSECT IRRRCHQJ in IRRRCH16)

- Error restoring cache
 - Service name: RESTORE
 - Variable data: Restore: IRRRCH12 Restore DS error

R cachesery (CSECT IRRRCH18)

- Unable to use ICSF for random number generation, therefore, a software pseudo random number generator (SW PRNG) will be used. It is possible that CSNBRNG is not found in LPA. See 'FINDMOD:' logrec for more information.
 - Service name: RANDNUM
 - Variable Data: IRRRCH18: USING SW PRNG, NOT CSNBRNG
 - Primary symptom string return code: 4
 - Primary symptom string reason code: 0
- Unable to find module in LPA using CSVQUERY
 - Service name: name of the module that was not found
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd FINDMOD: UNABLE TO FIND MODULE IN LPA.
 - aaaaaaa is an indicator of R_cacheserv operation. The following are possible values for aaaaaaaa:

Table 33. Indicator of R_cacheserv operation

аааааааа	Operation
201	IRRRCH10 SRB failed
202	Find IRRRCH10 SRB in LPA
203	Find other module in LPA (CSNBRNG)
210	Get cell from cell pool in data space
211	Add cell pool extent to cell pool in data space
213	Copy data to data cell(s) in cell pool
214	Locate data in data space
215	Delete data in data space
216	R18ADD
217	R18IDX
218	R18GET
219	GenerateReference

Table 33. Indicator of R_cacheserv operation (continued)

aaaaaaaa	Operation
220	CallDes

- bbbbbbbb is the system service or internal check being performed. The following are possible values for *bbbbbbbb*:

Table 34. System service or internal check being performed

bbbbbbbb	Service
8	DSPSERV create - Create data space
10	CSRPGT1 – Get cell pool cell
11	CSRPEXP – Add cell pool extent
12	ALESERV Add
13	CHKEXT – Check if data space is full (does EXTent area hit data area)
14	Search – Find node in cache
15	PLO instruction #1
16	DSPSERV delete – delete data space
17	PLO instruction #2
18	CSRPFR1 – Free cell pool cell (dddddddd = address of cell being freed)
19	Not used
20	Expiration time check for data or reference
21	CSNBRNG - ICSF random number function
22	Not used
23	CSVQUERY - Find mod in LPA
24	RACROUTE TYPE=ENCRYPT

- ccccccc is return code from service bbbbbbbb.
- dddddddd is reason code from service bbbbbbbb.
- Primary symptom string return code: 4
- Primary symptom string reason code: 0
- CSNBRNG failure, using software pseudo random number generator (PRNG)
 - Service name: RANDNUM
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd GENREF: USE SOFTWARE PRNG, NOT CSNBRNG
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - dddddddd = reason code from service bbbbbbbb
 - Primary symptom string return code: 0
 - Primary symptom string reason code: 0
- RACROUTE TYPE=ENCRYPT failure
 - Service name: CALLDES

- Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd RACROUTE REQ=EXTRACT, TYPE=ENCRYPT FAIL
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - dddddddd = reason code from service bbbbbbbb
- Primary symptom string return code: RACROUTE return code
- Primary symptom string reason code: 0

R cachesery (CSECT IRRCH20)

- Name/token service failure
 - Service name: [IEANTRT0 | IEANTRT1 | IEANTCR]
 - Variable data: SETUPCACHE: [IEANTRT|IEANTCR] FAILURE
 - Primary symptom string return code: return code from IEANTRT/IEANTCR
 - Primary symptom string reason code: 0 (name/token functions have no reason codes)
- · Failure due to no RCVI
 - Service name: FINDRCVI
 - Variable data: RCVTRCVI=0. UNABLE TO BUILD ICTX
 - Primary symptom string return code: 0
 - Primary symptom string reason code: 0
- · Error occurred during STORE operation
 - Service name: STORE
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORE: R18ADD ([1|2]) ERROR
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - dddddddd = reason code from service bbbbbbbb
 - Primary symptom string return code: [0,4,8...]
 - Primary symptom string reason code: 0
- Error occurred while an R_cacheserv operation was trying to find or create the cache
 - Service name: IRRRCH18
 - Variable Data: aaaaaaa bbbbbbbb ccccccc dddddddd SETUPCACHE: **ERROR IN IRRRCH18**
 - aaaaaaaa = indicator of R cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - dddddddd = reason code from service bbbbbbbb
 - Primary symptom string return code: [0,4,8...]

- Primary symptom string reason code: 0
- Error occurred during DESTROY operation
 - Service name: DESTROY
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd DESTROY: R18TERM ERROR
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - dddddddd = reason code from service bbbbbbbb
 - Primary symptom string return code: [0,4,8...]
 - Primary symptom string reason code: 0
- · Error occurred during RETRIEVE operation
 - Service name: RETRIEVE
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd RETRIEVE: **R18GET ERROR**
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - dddddddd = reason code from service bbbbbbbb
 - Primary symptom string return code: [0,4,8...]
 - Primary symptom string reason code: 0
- Error occurred during REMOVE operation
 - Service name: REMOVE
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORE: R18DEL **ERROR**
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - *dddddddd* = reason code from service *bbbbbbbb*
 - Primary symptom string return code: [0,4,8...]
 - Primary symptom string reason code: 0
- Error occurred during REMOVE EXPIRED operation
 - Service name: CLEANUP
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORE: R18CLN **ERROR**
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb

- dddddddd = reason code from service bbbbbbbb
- Primary symptom string return code: [0,4,8...]
- Primary symptom string reason code: 0
- Error occurred during LOCATE operation
 - Service name: LOCATE
 - Variable Data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORE: R18IDX **ERROR**
 - aaaaaaaa = indicator of R_cacheserv operation See Table 33 for possible values.
 - bbbbbbbb = system service or internal check being performed See Table 34 for possible values.
 - ccccccc = return code from service bbbbbbbb
 - dddddddd = reason code from service bbbbbbbb
 - Primary symptom string return code: [0,4,8...]
 - Primary symptom string reason code: 0

R cachesery (CSECT IRRCH22)

- Error occurred obtaining storage for a DSG block
 - Service name: OBTAIN1
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORAGE OBTAIN FOR DSG FAILURE
 - aaaaaaaa = STORAGE OBTAIN length
 - bbbbbbbb = STORAGE OBTAIN subpool
 - ccccccc = unused
 - dddddddd = unused
 - Primary symptom string return code: storage obtain return code. See z/OS MVS Programming: Assembler Services Reference IAR-XCT for the description of the return codes for the STORAGE OBTAIN macro.
 - Primary symptom string reason code: 0
- · No active TTAB was found
 - Service name: TTAB1
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd NO ACTIVE TTAB **FOUND**
 - aaaaaaaa = address of the DSCA
 - bbbbbbbbb = TTAB anchor
 - ccccccc = active TTAB pointer
 - *dddddddd* = unused
 - Primary symptom string return code: 0
 - Primary symptom string reason code: 0
- Inconsistency found in TTAB slot
 - Service name: MEMTOKCK
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd TTAB SLOT **INCONSISTENCY** system-name
 - aaaaaaaa = TTAB anchor
 - bbbbbbbb = active TTAB pointer
 - ccccccc = index into the active TTAB
 - dddddddd = system token for system name

- system-name = system name of sysplex member
- Primary symptom string return code: 0
- Primary symptom string reason code: 0
- DSG has been returned with either no DSGR or more than one DSGR
 - Service name: DSG2
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd DSG INCONSISTENCY FROM SYSTEM system-name
 - aaaaaaaa = DSG address
 - bbbbbbbb = DSG return code
 - ccccccc = DSGR pointer
 - dddddddd = number of responses
 - system-name = system name of sysplex member
 - Primary symptom string return code: 0
 - Primary symptom string reason code: 0
- · Error occurred when attempting intersystem communication
 - Service name: DSG1
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd UNEXPECTED DSG RC FROM SYSTEM system-name
 - aaaaaaaa = DSG address
 - bbbbbbbb = DSG return code
 - ccccccc = number of DSGs sent
 - dddddddd = DSGR pointer
 - system-name = system name of sysplex member
 - Primary symptom string return code: 0
 - Primary symptom string reason code: 0
- Other system had either: more information to return and had a STORAGE OBTAIN error, or an unexpected error
 - Service name: IRRRCH24
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd IRRRCH24 HAD PROBLEM ON SYSTEM system-name
 - aaaaaaaa = DSG address
 - bbbbbbbbb = DSGR pointer
 - *ccccccc* = DSGR return buffer pointer
 - dddddddd = DSGR return buffer length
 - system-name = system name of sysplex member
 - Primary symptom string return code: IRRRCH24 return code
 - 2 BAD OBTAIN, STORAGE OBTAIN failure
 - Primary symptom string reason code: IRRRCH24 reason code
 - When IRRRCH24 return code = 2, storage obtain return code See z/OS MVS Programming: Assembler Services Reference IAR-XCT for the description of the return codes for the STORAGE OBTAIN macro.
- · The DSGR lacks a return buffer
 - Service name: DSGR1
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd DSGR LACKS RETURN BUFFER FROM system-name
 - aaaaaaaa = DSG address

- bbbbbbbb = DSGR pointer
- ccccccc = DSGR return buffer pointer
- dddddddd = DSGR return buffer length
- system-name = system name of sysplex member
- Primary symptom string return code: 0
- Primary symptom string reason code: 0
- STORAGE OBTAIN failure on R_cacheserv return buffer for record name
 - Service name: OBTAIN2
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORAGE OBTAIN FOR RECORD NAME FAILURE
 - aaaaaaaa = STORAGE OBTAIN length
 - bbbbbbbb = STORAGE OBTAIN subpool
 - ccccccc = unused
 - dddddddd = unused
 - Primary symptom string return code: storage obtain return code. See z/OS MVS Programming: Assembler Services Reference IAR-XCT for the description of the return codes for the STORAGE OBTAIN macro.
 - Primary symptom string reason code: 0
- STORAGE OBTAIN failure on R cacheserv return buffer for date
 - Service name: OBTAIN3
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORAGE **OBTAIN FOR DATA FAILURE**
 - aaaaaaaa = STORAGE OBTAIN length
 - bbbbbbbb = STORAGE OBTAIN subpool
 - ccccccc = unused
 - dddddddd = unused
 - Primary symptom string return code: storage obtain return code. See z/OS MVS Programming: Assembler Services Reference IAR-XCT for the description of the return codes for the STORAGE OBTAIN macro.
 - Primary symptom string reason code: 0
- STORAGE OBTAIN failure on R_cacheserv return buffer for source
 - Service name: OBTAIN4
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd STORAGE **OBTAIN FOR SOURCE FAILURE**
 - aaaaaaaa = STORAGE OBTAIN length
 - bbbbbbbb = STORAGE OBTAIN subpool
 - ccccccc = unused
 - dddddddd = unused
 - Primary symptom string return code: storage obtain return code. See z/OS MVS Programming: Assembler Services Reference IAR-XCT for the description of the return codes for the STORAGE OBTAIN macro.
 - Primary symptom string reason code: 0
- · Error from a R_cacheserv operation on another system
 - Service name: IRRRCH24
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd **xx password ERROR ON SYSTEM system-name
 - aaaaaaaa = R cacheserv option

- bbbbbbbbb = unused
- ccccccc = unused
- dddddddd = unused
- **xx = 1st 4 characters of input userid
- password = input password
- system-name = system name of sysplex member
- Primary symptom string return code: system-name R_cacheserv RACF return code
- Primary symptom string reason code: system-name R_cacheserv RACF reason code
- IRRRCH22 had an unknown return code
 - Service name: WAYOUT
 - Variable data: aaaaaaaa bbbbbbbb ccccccc dddddddd **xx password **INTERNAL ERROR**
 - aaaaaaaa = R_cacheserv option
 - bbbbbbbb = unused
 - ccccccc = unused
 - dddddddd = unused
 - **xx = 1st 4 characters of input userid
 - password = input password
 - Primary symptom string return code: unexpected IRRRCH22 return code
 - Primary symptom string reason code: unexpected IRRRCH22 reason code

R Datalib (CSECT IRRRDL04)

- Error determining the owning user ID for a DIGTCERT profile
 - Service name: RACXTRT
 - Variable data: The string 'Method GETUSERID failed to extract the UserID'
 - Additional variable data: The profile name
- Error incrementing the last serial number (CERTLSER) of a DIGTCERT profile
 - Service name: RACXTRT or ICHEINTY
 - Variable data: The string 'Module IRRCDC29 failed to generate new Serial Number'
 - Additional variable data: The profile name

R_Datalib (CSECT IRRRDL06)

- · Error parsing the input certificate
 - Service name: IRRCDC03
 - Variable data: The string 'IRRCDC03 failed to parse the certificate'
- · Error retrieving the certificate profile
 - Service name: BACMAP
 - Variable data: The string 'RACMAP failed to retrieve the certificate profile'
 - Additional variable data: The certificate profile name
- · Error retrieving the CERTNAME repeat group from a user profile
 - Service name: RACEXTR

- Variable data: The string 'RACEXTR failed to retrieve the CERTNAME repeat group'
- Additional variable data: The user name
- Error locating the certificate in the CERTNAME repeat group
 - Service name: RACEXTR
 - Variable data: The String 'Certificate not found in USER profile'
 - Additional variable data: The user name
- Error retrieving the private key from the certificate profile
 - Service name: RACEXTR
 - Variable data: The string 'RACFEXTR failed to retrieve the private key'
 - Additional variable data: The certificate profile name
- Error adding the certificate to RACF
 - Service name: IRRCDC02
 - Variable data: The string 'IRRCDC02 Error Certificate already exists'
 - Additional variable data: The certificate profile name
- · Error adding the certificate to RACF
 - Service name: IRRCDC02
 - Variable data: The string 'IRRCDC02 failed to add the certificate'
 - Additional variable data: The certificate profile name
- · Error altering the certificate in RACF
 - Service name: IRRCDC05
 - Variable data: The string 'IRRCDC05 failed to alter the certificate'
 - Additional variable data: The certificate profile name
- Error connecting the certificate to a RACF ring
 - Service name: IRRCDC19
 - Variable data: The string 'IRRCDC19 failed to connect the certificate'
 - Additional variable data: The certificate profile name
- Error calling ICSF service CSNDKRR to retrieve the PKDS entry
 - Service name: CSNDKRR
 - Variable data: The string 'CSNDKRR failed to retrieve the PKDS entry'
 - Additional variable data: The PKDS entry name

R_DCEAUTH (CSECT IRRRDA00)

- Create ACEE failure
 - Service name: RACINIT
 - Variable data: the RACF user ID
- · Convert UUID to RACF user ID failure
 - Service name: RACXTRT
 - Variable data: the DCEUUIDS profile name
- · Check authorization failure
 - Service name: RACHECK or FASTAUTH
 - Variable data: the RACF user ID, class, profile, and access requested
- · Delete ACEE failure
 - Service name: RACINIT
 - Variable data: the ACEE address

R DCEINFO (CSECT IRRRDI00)

Error recording

- · Extract DCE fields failure
 - Service name: RACXTRT
 - Variable data: the RACF user ID and the names of the fields
- Replace DCE fields failure
 - Service name: RACXTRT
 - Variable data: the RACF user ID and the names of the fields

R_DCERUID (CSECT IRRRUD00)

- Extract DCEUUIDS APPLDATA failure
 - Service name: RACXTRT
 - Variable data: the DCEUUIDS profile name

R_DCEKEY (CSECT IRRRDK00)

- Extract DCE key failure
 - Service name: RACXTRT
 - Variable data: the RACF user ID
- Replace DCE key failure
 - Service name: RACXTRT
 - Variable data: the RACF user ID

R DCEKEY (CSECT IRRCPT01)

- · Extract KEYSMSTR key failure
 - Service name: ICHEINTY
 - Variable data: the class and profile name
- ICSF CSNBENC callable service failure
 - Service name: CSNBENC
 - Variable data: the RACF user ID
- · ICSF CSNBDEC callable service failure
 - Service name: CSNBDEC
 - Variable data: the RACF user ID

R_PKIserv (CSECT IRRRPX00)

- · Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R_PKIserv attempting to check a caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the user ID from the ACEE

R_PKIserv (CSECT IRRRPX02)

- Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R PKIserv GENCERT attempting to check a caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the user ID from the ACEE
- Unexpected return code from RACDCERT internal subroutine IRRCDC23
 - Service name: IRRCDC23

- Variable data: The string 'Error in R_PKIserv GENCERT attempting to call RACDCERT subroutine. Unexpected return code'
- Additional variable data: The first 942 bytes of the RACDCERT internal work area
- Error calling RACROUTE REQUEST=EXTRACT to retrieve the PGMRNAME field from the USER profile
 - Service name: RACXTRT
 - Variable data: The string 'Error in R_PKIserv GENCERT attempting to extract PGMRNAME field to build Common Name'
 - Additional variable data: The user ID

R_PKIserv (CSECT IRRRPX04)

- Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R PKIserv EXPORT attempting to check the caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the user ID from the ACEE
- Unexpected return code from RACDCERT internal subroutine IRRCDC25
 - Service name: IRRCDC25
 - Variable data: The string 'Error in R PKIserv EXPORT attempting to call RACDCERT subroutine. Unexpected return code'
 - Additional variable data: The first 942 bytes of the RACDCERT internal work area

R_PKIserv (CSECT IRRRPX06)

- · Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R_PKIserv GENCERT attempting to check the caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the user ID from the ACEE
- Unexpected return code from RACDCERT internal subroutine IRRCDC27
 - Service name: IRRCDC27
 - Variable data: The string 'Error in R_PKIserv GENCERT attempting to call RACDCERT subroutine. Unexpected return code'
 - Additional variable data: The first 942 bytes of the RACDCERT internal work area
- Error calling RACROUTE REQUEST=EXTRACT to retrieve the PGMRNAME. field from the USER profile
 - Service name: RACXTRT
 - Variable data: The string 'Error in R PKIserv GENCERT attempting to extract PGMRNAME field to build Common Name'
 - Additional variable data: The user ID
- Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token service failed'

- Additional variable data: The first 942 bytes of the RACDCERT internal work area
- Error on PC to PKI Services
 - Service name: PKIGENC
 - Variable data: The string 'PKI Services Failed for function GENCERT'
 - Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC

R_PKIserv (CSECT IRRRPX07)

- Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R_PKIserv EXPORT attempting to check the caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the user ID from the ACEE
- Error calling IRRCDC67 to find parent CERTAUTH chain to input certificate and build PKCS7 package.
 - Service name: IRRCDC67
 - Variable data: The string 'Error in R_PKIServ EXPORT attempting to call RACDCERT subroutine. Unexpected return code.'
 - Additional variable data: RACDCERT failing module and service in form of diagnostic data from the RACDCERT internal work area:
 - 4 bytes internal service code
 - 4 bytes service return code
 - 4 bytes service reason code
 - 8 bytes RACF class name
 - 8 bytes RACF segment name
 - 81 bytes blank
 - 8 bytes csect name
 - 71 bytes diagnostic message text
 - 4 bytes RACF entity length
 - 4 bytes number of extracted fields
 - 56 bytes array of 8 byte field names (max 7 entries)
 - 256 bytes RACF entity name
- Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token service failed'
 - Additional variable data: None
- · Error on PC to PKI Services
 - Service name: PKIEXPT
 - Variable data: The string 'PKI Services Failed for function EXPORT'
 - Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC

R PKIserv (CSECT IRRRPX08)

- Error calling MVS Name/Token Service
 - Service name: IEANTRT

- Variable data: The string 'Name/Token service failed'
- Additional variable data: None
- · Error on PC to PKI Services
 - Service name: PKIQRYR or PKIQRYC
 - Variable data: The string 'PKI Services Failed for function {QUERYREQS | QUERYCERTS}'
 - Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC

R_PKIserv (CSECT IRRRPX10)

- Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token service failed'
 - Additional variable data: None
- · Error on PC to PKI Services
 - Service name: PKICRTR or PKICRTD
 - Variable data: The string 'PKI Services Failed for function {REQDETAILS | CERTDETAILS}'
 - Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC

R PKIserv (CSECT IRRRPX12)

- · Error on PC to PKI Services
 - Service name: PKIMODR or PKIMODC
 - Variable data: The string 'PKI Services Failed for function (MODIFYREQS) | MODIFYCERTS}'
 - Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC
- Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token service failed'
 - Additional variable data: None

R PKIserv (CSECT IRRRPX13)

- Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R_PKIServ VERIFY attempting to check the caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the User ID from the ACEE
- Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token service failed'
 - Additional variable data: None
- · Error on PC to PKI Services
 - Service name: PKIVERF
 - Variable data: The string 'PKI Services Failed for function VERIFY'

 Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC

R_PKIserv (CSECT IRRRPX14)

- Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R_PKIServ REVOKE attempting to check the caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the User ID from the ACEE
- Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token service failed'
 - Additional variable data: None
- · Error on PC to PKI Services
 - Service name: PKIREVOKE
 - Variable data: The string 'PKI Services Failed for function REVOKE'
 - Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC

R PKIserv (CSECT IRRRPX15)

- Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R_PKIServ RENEW attempting to check the caller's authority to the service'
 - Additional variable data: The FACILITY class profile name, the ACEE address, and the User ID from the ACEE
- Error on PC to PKI Services
 - Service name: PKIRENW
 - Variable data: The string 'PKI Services Failed for function RENEW'
 - Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC
- Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token service failed'
 - Additional variable data: None

R PKIserv (CSECT IRRRPX18)

- Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile
 - Service name: RACHECK
 - Variable data: The string 'Error in R PKIServ RESPOND attempting to check the caller's authority to the service'
 - The FACILITY class profile name, the ACEE address, the User ID from the ACEE
- · Error calling MVS Name/Token Service
 - Service name: IEANTRT
 - Variable data: The string 'Name/Token Service, IEANTRT, failed'

Services (register 1) followed by the parameter list used on the PC. R_PKIserv (CSECT IRRRPX20) I Error calling RACROUTE REQUEST=AUTH to determine the caller's access to a FACILITY class profile Service name: RACHECK Variable data: The string 'Error in R_PKIServ SCEPREQ attempting to check the caller's authority to the service' Additional variable data: The FACILITY class profile name, the ACEE address, the User ID from the ACEE · Error calling MVS Name/Token Service Service name: IEANTRT Variable data: The string 'Name/Token Service, IEANTRT, failed' Additional variable data: None · Error on PC to PKI Services - Service name: R PKIServ PKISCEP Variable data: The string 'PKI Services failed for function SCEPREQ' Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC. R PKIserv (CSECT IRRRPX22) Error calling MVS Name/Token Service Service name: IEANTRT Variable data: The string 'Name/Token Service, IEANTRT, failed' Additional variable data: None · Error on PC to PKI Services Service name: R_PKIServ PKIPREG Variable data: The string 'PKI Services failed for function PREREGISTER' Additional variable data: Additional information word returned from PKI Services (register 1) followed by the parameter list used on the PC. R_proxyserv (CSECT IRRRPY00)

Additional variable data: None

Service name: R_PKIServ RESPOND

 Variable data: The string 'PKI Services failed for function RESPOND' Additional variable data: Additional information word returned from PKI

· Error on PC to PKI Services

R_proxyserv (CSECT IRRRPY01 and IRRRPY02)

Error response from LDAP

· Name/token service failure Service name: IEANTRT

- Service name: LDAP
- Variable data: Up to 100 bytes of the LDAP error message

 Variable data: The string "Name/token service failure" Additional variable data: The name for the requested token

- · LDAP message response decoding failure
 - Service name: LDAPMSG
 - Variable data: One of the following strings –

Error recording

- "Error in LDAP message Incorrect ASN.1 syntax"
- "Error in LDAP message Expected field not found"
- "Error in LDAP message Unsupported character set detected"
- Additional variable data: Up to 1024 bytes of the returned LDAP message

R_proxyserv (CSECT IRRCPT01)

- Extract KEYSMSTR key failure
 - Service name: ICHEINTY
 - Variable data: the class and profile name
- ICSF CSNBENC callable service failure
 - Service name: CSNBENC
 - Variable data: the RACF user ID
- · ICSF CSNBDEC callable service failure
 - Service name: CSNBDEC
 - Variable data: the RACF user ID

R admin (CSECT IRRREQ00)

 The R admin callable service makes use of the RACF subsystem address space. RACF command images generated by the callable service or by the caller are passed to the RACF subsystem for execution by invoking the internal macro IRRREQ. The IRRREQ macro utilizes the IEFSSREQ macro to communicate with the RACF subsystem.

In this environment the following errors could occur:

- IRRREQ is unable to communicate with the RACF subsystem (for example, the RACF subsystem hasn't been started).
- IRRREQ is able to communicate with the RACF subsystem, but the RACF command fails in the RACF subsystem (for example, an ADDUSER command specifying a class that is not valid).
- The R admin callable service differentiates between these two errors. For the first error, the callable service returns a SAF return code of 8, a RACF return code of 12, and a RACF reason code set equal to the return code from IEFSSREQ. For the second error, the callable service returns a SAF return code of 8, a RACF return code of 16, and a RACF reason code set equal to the return code returned from the command's execution in the RACF subsystem. Additionally, the R_admin callable service writes symptom records to SYS1.LOGREC for the errors. The symptom records contain the following information:
 - Primary symptom string:
 - Component identifier (PIDS) 5752XXH00
 - 1st return code (PRCS) RACF return code from the callable service
 - 2nd return code (PRCS) RACF reason code from the callable service
 - Csect routine identifier (RIDS) IRRREQ00
 - Loadmod routine identifier (RIDS) IRRRFR10#L
 - Secondary symptom string:
 - Storage address (ADRS) Error offset into IRRREQ00
 - Free format component information: Specific to the error

For the first error (unable to communicate with the RACF subsystem), RACF records the following additional information in the free format area:

Error recording

Offset	Length	Description
0	1	R_admin callable service function requested
1	4	Address of the command image to be executed
5	2	Length of the command image to be executed

Figure 51 shows an example of a symptom record created when the R_admin callable service is unable to communicate with the RACF subsystem.

```
TYPE: SYMPTOM RECORD REPORT: SOFTWARE EDIT REPORT DAY YEAR
                                    REPORT DATE: 348 96
SCP:
      VS 2 REL 3
                                     ERROR DATE: 348
                                                     96
                                                          HH MM SS.TH
                    MODEL: 4381
                    SERIAL: 111606
                                                    TIME: 15:24:51.20
SEARCH ARGUMENT ABSTRACT:
   PIDS/5752XXH00 PRCS/0000000C PRCS/00000004 RIDS/IRRREQ00
   RIDS/IRRRFR10#L
SYSTEM ENVIRONMENT:
   CPU MODEL: 4381
                                DATE: 348 96
   CPU SERIAL: 111606
                                TIME: 15:24:51.20
   SYSTEM:
              NODE1
                                BCP:
                                       MVS
   RELEASE LEVEL OF SERVICE ROUTINE:
                                        JBB6604
   SYSTEM DATA AT ARCHITECTURE LEVEL:
   COMPONENT DATA AT ARCHITECTURE LEVEL: 10
   SYSTEM DATA: 00000000 00000000
COMPONENT INFORMATION:
   COMPONENT ID:
                            5752XXH00
   COMPONENT RELEASE LEVEL: 240
   SERVICE RELEASE LEVEL:
                            HRF2240
   DESCRIPTION OF FUNCTION: RACF z/OS UNIX SYSTEM CALLABLE SERV.
   PROBLEM ID:
                            IRRREQ
PRIMARY SYMPTOM STRING:
   PIDS/5752XXH00 PRCS/0000000C PRCS/00000004 RIDS/IRRREQ00
   RIDS/IRRRFR10#L
   SYMPTOM
                     SYMPTOM DATA
                                     EXPLANATION
                    COMPONENT IDENTIFIER
   PIDS/5752XXH00
   PRCS/0000000C
                   00000004
IRRREQ00
   PRCS/00000004
   RIDS/IRRRE000
                                     ROUTINE IDENTIFIER
   RIDS/IRRRFR10#L IRRRFR10#L
                                     ROUTINE IDENTIFIER
SECONDARY SYMPTOM STRING:
   ADRS/00000734
   SYMPTOM
                     SYMPTOM DATA
                                     EXPLANATION
                     -----
                                     -----
   ADRS/00000734
                     00000734
                                     STORAGE ADDRESS
FREE FORMAT COMPONENT INFORMATION:
KEY = F000 LENGTH = 000100 (0064)
+000 0204803C A2000D40 40404040
                                        40404040
                                                    |....S...
+010 LENGTH(0080) ==> ALL BYTES CONTAIN X'40'.
+060
      40404040
```

Figure 51. An Example of a Symptom Record when the Callable Service Cannot Communicate with RACF

The IRRREQ (IEFSSREQ) return code is 4. Looking at the free format component information, the first byte has a value of X'02', indicating this was an ADMN_DEL_USER request. The next 4 bytes contain the address of the generated command image (X'04803CA2'). The sixth and seventh bytes contain the two byte length of the generated command image (X'000D').

For the second error (execution of the RACF command failed), the main intent of the symptom record is to capture the command image that was executed, because it might not be available elsewhere. Therefore, to limit the amount of user error information written to SYS1.LOGREC, RACF does not write symptom records for ADMN_RUN_COMD requests that fail. RACF also does not write symptom records for ADMN_ADD_USER requests where the RACF user ID already exists and ADMN_DEL_USER requests where the

RACF user ID doesn't exist. For the cases where RACF does write a symptom record, the following additional information is recorded in the free format area:

- First X'64' byte area-Command message output (if any). This is the first message text string only and is truncated if it exceeds X'64' bytes in length.
- Next four X'100' byte areas—A copy of the command image that was executed. The command image is truncated if it exceeds 1024 (decimal) bytes in length.

You can trace the R_admin callable service to obtain information not included in the symptom records. For information on tracing, see Tracing the R_admin callable service.

Figure 52 shows an example of a symptom record created when the R_admin callable service is able to communicate with the RACF subsystem, but the command fails.

Error recording

```
TYPE: SYMPTOM RECORD
                         REPORT: SOFTWARE EDIT REPORT DAY YEAR
                         REPORT DATE:
                                      014 97
SCP:
      VS 2 REL 3
                         ERROR DATE:
                                         014 97
                         MODEL: 4381
                                         HH MM
                                                   SS.TH
                         SERIAL: 111606 TIME: 10:24:10.11
SEARCH ARGUMENT ABSTRACT:
   PIDS/5752XXH00 PRCS/00000010 PRCS/00000008 RIDS/IRRREQ00
   RIDS/IRRRFR10#L
   SYSTEM ENVIRONMENT:
   CPU MODEL: 4381
                                 DATE: 014 97
   CPU SERIAL: 111606
                                 TIME: 10:24:10.11
   SYSTEM:
               NODE1
                                 BCP:
                                        MVS
   RELEASE LEVEL OF SERVICE ROUTINE:
                                         JBB6604
   SYSTEM DATA AT ARCHITECTURE LEVEL:
                                         10
   COMPONENT DATA AT ARCHITECTURE LEVEL: 10
   SYSTEM DATA: 00000000 00000000
COMPONENT INFORMATION:
   COMPONENT ID:
                             5752XXH00
   COMPONENT RELEASE LEVEL: 240
                             HRF2240
   SERVICE RELEASE LEVEL:
   DESCRIPTION OF FUNCTION: RACF z/OS UNIX SYSTEM CALLABLE SERV.
   PROBLEM ID:
                             IRRRE0
   PRIMARY SYMPTOM STRING:
   PIDS/5752XXH00 PRCS/00000010 PRCS/00000008 RIDS/IRRREQ00
   RIDS/IRRRFR10#L
   SYMPTOM
                      SYMPTOM DATA
                                      EXPLANATION
                      -----
                                      COMPONENT IDENTIFIER
   PIDS/5752XXH00
                      5752XXH00
   PRCS/00000010
                     00000010
                                      RETURN CODE
   PRCS/00000008
                     80000008
                                      RETURN CODE
   RIDS/IRRREQ00
                     IRRREQ00
                                      ROUTINE IDENTIFIER
   RIDS/IRRRFR10#L
                     IRRRFR10#L
                                      ROUTINE IDENTIFIER
   SECONDARY SYMPTOM STRING:
   ADRS/00000748
   SYMPTOM
                      SYMPTOM DATA
                                      EXPLANATION
                      -----
    -----
                                      -----
   ADRS/00000748
                      00000748
                                      STORAGE ADDRESS
FREE FORMAT COMPONENT INFORMATION:
KEY = F000
               LENGTH = 000100 (0064)
                F6F7F0F2
                           C940C9D5
+000
      C9D2D1F5
                                         E5C1D3C9
                                                     IKJ56702I INVALI
+010
                                                      D CLASS NAME, BA
      C440C3D3
                 C1F2F240
                             D5C1D4C5
                                         6B40C2C1
+020
      C4C3D3C1
                 E2E24040
                             40404040
                                         40404040
                                                     DCLASS
+030 LENGTH(0048) ==> ALL BYTES CONTAIN X'40'.
+060
       40404040
KEY = F000
               LENGTH = 000256 (0100)
                                                     ADDUSER GUMBY
       C1C4C4E4
                 E2C5D940 C7E4D4C2
                                          E8404040
+000
+010
       4040D5C1
                   D4C54040
                              40404040
                                          40404D7D
                                                       NAME
       D1968895
                   40D84B40 C7A49482
                                          A87D5D40
                                                      JOHN Q. GUMBY')
+020
+030
       404040C3
                   D3C1E4E3
                              C8404040
                                          4040404D
                                                       CLAUTH
+040
       82818483
                   9381A2A2
                              5D40D7C1
                                          E2E2E6D6
                                                      BADCLASS) PASSWO
+050
       D9C44040
                   40404DA7
                              A7A75D40
                                          C1C4C4C3
                                                      RD
                                                          (XXX) ADDC
+060
       C1E3C5C7
                   D6D9E840
                              4040404D
                                          8381A3F1
                                                      ATEGORY
                                                                 (CAT1
+070
       5D404040
                   40404040
                              40404040
                                          40404040
+080 LENGTH(0128) ==> ALL BYTES CONTAIN X'40'.
```

Figure 52. An Example of a Symptom Record when a Command Fails

In this example, the RACF subsystem return code is 8. In the free format component information, the first X'64' byte area contains the diagnostic message ("IKJ56702I INVALID CLASS NAME, BADCLASS") produced by executing the command image. The next four X'100' areas (only 1 in this

case) contain the command image itself (ADDUSER GUMBY NAME ('JOHN Q. GUMBY') CLAUTH(BADCLASS) PASSWORD(XXX) ADDCATEGORY(CAT1)). Note that the actual password value is not recorded.

Control Block overviews for RACF

This presents the links between control blocks that can be useful when diagnosing problems related to RACF.

RCVT and SAF Router Vector Table




Figure 53. Control Block Overview: RCVT and SAF Router Vector Table

ACEE and related Control Blocks

The first time a RACROUTE REQUEST=VERIFY is issued for an address space, there is only one ACEE (accessor environment element), and it is pointed to by the ASXB (see Figure 54).

For any subsequent task in the address space (multiple users), the following cases could occur:

- A table of pointers to ACEEs is set up in the address space. This occurs for CICS (Customer Information Control System) or IMS (Information Management System) address spaces.
- Another ACEE is created when the VERIFY request is issued. This ACEE is pointed to only by the TCB for that task. See Figure 55.

Control Block overviews

 When a third-party AUTH request is used (USERID was specified on the RACROUTE REQUEST=AUTH), the ACEE is pointed to by an existing ACEE. See Figure 56.

For more information on how ACEEs are created and which ACEE is used, see *z/OS Security Server RACF System Programmer's Guide*.




Figure 54. Control Block Overview: ACEE in a Single-User Address Space




Figure 55. Control Block Overview: ACEE in a Multiple-User Address Space




Figure 56. Control Block Overview: ACEEs When Third-Party AUTH Request Is Used

SVC dump title descriptions

This describes the SVC (supervisor call instruction) dumps generated by RACF recovery routines.

SVC failure (ICHRST00)

This SVC dump issued by RACF has the form:

ICHRST00—RACF SVCS, ABEND CODE=sss-rrr, SVC=svcname, USER=RACF user ID or job name, GROUP=RACF group ID or step name[, EXIT= csectname]

Component:

Resource Access Control Facility (RACF), 5752-XXH00

Issuing Module:

ICHRST00—ESTAE

Explanation:

An abend has occurred during processing of one of the RACF SVCs or during processing of the GENLIST or RACLIST operand of the SETROPTS command. The values in the system dump title are:

SSS

System completion code (abend code), in hexadecimal.

rrr Reason code associated with the system completion code (described in z/OS Security Server RACF Data Areas).

svcname

Name of the RACF routine handling the SVC and issuing the abend.

RACF user ID or job name

If interactive, RACF user ID of user who encountered the problem.

If batch, then name of job that encountered the problem.

RACF group ID or step name

If interactive, RACF group of user who encountered the problem.

If batch, then name of step that encountered the problem.

csectname

Name of the CSECT that probably caused the error.

System Action:

The executing task is terminated. The areas dumped are PSA, RGN, LPA, TRT, CSA, and SQA.

Problem Determination:

- 1. Look for the EXIT shown in the dump title:
 - If the EXIT shown in the system dump title is an installation exit, the installation exit probably caused the error (for a description of installation exits, see z/OS Security Server RACF System Programmer's Guide). Debug the installation exit. You can use standard debugging methods to analyze the problem described in this system dump.
 - If the EXIT shown in the system dump title is an IBM routine, or if EXIT is missing from the system dump title, follow the remaining steps in this procedure.
- 2. Look for message ICH409I as issued for this system dump. See the message text for the following:
 - Abend code and reason code (must be the same as in the dump title)
 - · RACF macro or SETROPTS command option (GENLIST or RACLIST) that was being processed
 - Whether parameter validation or other processing was being done See z/OS Security Server RACF Messages and Codes for an explanation of ICH409I and of the abend code (and its reason code, if supplied).
- 3. If ICH409I is not available, see z/OS Security Server RACF Messages and Codes for an explanation of the abend code (sss) and reason code (rrr) from the dump title.
- 4. If the explanation of the code does not help you solve the problem and the EXIT named in the system dump title is an IBM routine, see Abend troubleshooting table for instructions on debugging the problem.

SVC dump descriptions

Other Problem Data Produced:

A software record is written to SYS1.LOGREC and includes:

Main CSECT (control section) name of SVC **SDWAMODN**

(supervisor call instruction)

SDWACSCT Blanks or name of routine in control at time

of error

SDWAREXN ICHRST00 (recovery routine)

SDWAGR15 Reason code if the abend is a RACF abend

SDWACRC Completion code

SDWACID XXH00

SDWAEAS 1 if SDUMP is generated by ICHRST00

SDWAREQ Zero if SDUMP is generated by ICHRST00

RACF initialization failure (ICHSEC02)

The form of this dump issued by RACF depends on the cause of the dump.

Component:

Resource Access Control Facility (RACF), 5752-XXH00

Issuing Module:

ICHSEC02—ESTAE

Explanation:

An abend has occurred during RACF initialization processing. The areas dumped are SQA, CSA, NUC, and RGN.

Problem Determination:

- 1. See message ICH505A for the abend code that caused the system dump.
- 2. If message ICH529I was issued, an RVARY command failed.
- 3. See z/OS Security Server RACF Messages and Codes for an explanation of the abend code and the messages.
- 4. If the explanations in *z/OS Security Server RACF Messages and Codes* do not help you solve the problem, see Abend troubleshooting table for instructions on debugging the problem.

Other Problem Data Produced:

A software record is written to SYS1.LOGREC and includes:

SDWAMODN ICHSEC00 (module detecting the error)

SDWAREXN ICHSEC02 (recovery routine)

SDWACID XXH00 **SDWACSCT** ICHSEC00

SDWAEAS 1 if SDUMP is generated by ICHSEC00

SDWAREQ Zero if SDUMP is generated by ICHSEC00

RACLIST failure (IRRCOP10)

This dump issued by RACF has the form:

IRRCOP10—RACF RACLIST TO A DATA SPACE FAILED FOR CLASS=classname

Component:

Resource Access Control Facility (RACF), 5752-XXH00

Issuing Module:

IRRCOP10—Copy RACLISTed Class to a Data Space

Explanation:

One of the following failed when attempting to copy the in-storage profiles into a data space during RACF initialization:

- SETROPTS RACLIST
- SETROPTS RACLIST REFRESH
- RACROUTE REQUEST=LIST,GLOBAL=YES request
- RACLIST

System Action:

The RACLIST for *classname* failed. A dump was taken to help determine the cause of the problem. Areas dumped are CSA, LSQA, and the data space.

Problem Determination:

- 1. Determine the cause of the failure by checking the return and reason codes provided by:
 - Message ICH14058I for the SETROPTS RACLIST or SETROPTS **RACLIST REFRESH cases**
 - Message ICH546I for the RACLIST during initialization case
 - Message IRRL0002I for the RACROUTE REQUEST=LIST,GLOBAL=YES case
- 2. Use standard debugging methods to analyze the dump itself. To look at a data space with IPCS, you must know the name of the data space. The name of a data space obtained for RACLIST purposes is "IRRxxxxx", where xxxxx is a hex number. The name of the data space in this dump can be obtained by an IPCS command, "listdump select". Simply scan the command's output for "DSPNAME" and use the resulting name and ASID to access the data space.

RACF COPY RACGLIST failure (IRRRLS12)

The form of this dump is:

IRRRLS12—RACF COPY RACGLIST classname nnnnn PROFILES FOR **CLASS**=*classname*

Component:

Resource Access Control Facility (RACF), 5752-XXH00

Issuing Module:

IRRRLS12—RACF RACGLIST to Data Space Routine

Explanation:

Problems were encountered while trying to read A RACGLIST classname_nnnnn profile in order to use the RACLIST results stored in those profiles to build the RACLIST data space for *classname*.

System Action:

In addition to taking this dump, RACF issues IRRL0000I, which identifies the specific profile and the manager return and reason codes for the failure. RACF proceeds to RACLIST classname by reading classname's discrete and generic profiles from the database to build the RACLIST results, which are then copied to the RACLIST data space. Areas dumped are SQA, LSQA, PSA, RGN, LPA, TRT, CSA, and SUMDUMP.

Problem Determination:

- 1. Determine the cause of the failure by checking the return and reason codes provided by message IRRL0000I.
- 2. Use standard debugging methods to analyze the dump itself.

RACF CREATE RACGLIST failure (IRRRLS13)

The form of this dump is:

IRRRLS13—RACF CREATE RACGLIST classname_nnnnn PROFILES FOR **CLASS**=*classname*

Component:

Resource Access Control Facility (RACF), 5752-XXH00

Issuing Module:

IRRRLS13—RACF Data Space to RACGLIST Routine

Explanation:

Problems were encountered while trying to write a RACGLIST classname nnnnn profile to the database after building a raclist data space while RACLISTing classname.

System Action:

In addition to taking this dump, RACF issues IRRL0000I, which identifies the specific profile and the manager return and reason codes for the failure. RACF attempts to delete all the RACGLIST classname nnnnn profiles. The RACLIST operation successfully built the RACLIST data space for classname. Areas dumped are SQA, LSQA, PSA, RGN, LPA, TRT, CSA, and SUMDUMP.

Problem Determination:

- 1. Determine the cause of the failure by checking the return and reason codes provided by message IRRL0000I.
- 2. Use standard debugging methods to analyze the dump itself.

RACF DELETE RACGLIST failure (IRRRLS14)

The form of this dump is:

IRRRLS14—RACF DELETE RACGLIST classname_nnnnn PROFILES FOR **CLASS**=*classname*

Component:

Resource Access Control Facility (RACF), 5752-XXH00

Issuing Module:

IRRRLS14—RACF Delete RACGLIST classname nnnnn

Explanation:

Problems were encountered while trying to delete a RACGLIST classname nnnnn profile from the database.

System Action:

In addition to taking this dump, RACF issues IRRL0000I, which identifies the specific profile and the manager return and reason codes for the failure.

If the command being processed was RDELETE RACGLIST classname, RACF terminates command processing. If the command was one of the commands or requests causing RACF to RACLIST classname, the RACLIST succeeded, but RACGLIST classname_nnnnn was not updated. Areas dumped are SQA, LSQA, PSA, RGN, LPA, TRT, CSA, and SUMDUMP.

Problem Determination:

- 1. Determine the cause of the failure by checking the return and codes provided by message IRRL0000I.
- 2. Use standard debugging methods to analyze the dump itself.

RACF data space recovery failure (IRRRLS15)

The form of this dump is:

IRRRLS15—RACF RACLIST TO A DATA SPACE RECOVERY FOR **CLASS**=*classname*

Component:

Resource Access Control Facility (RACF), 5752-XXH00

Issuing Module:

IRRRLS15—RACF RACLIST to Data Space Recovery

Explanation:

One of the following abended while processing a data space:

- SETROPTS RACLIST
- SETROPTS RACLIST REFRESH
- · RACLIST during initialization
- RACROUTE REQUEST=LIST, GLOBAL=YES

The ICHRST00 dump described in topic 224 is also taken. This dump provides the data space, which is not provided by the ICHRST00 dump.

System Action:

The command or request failed. A dump was taken to determine the cause of the problem. Areas dumped are CSA, LSQA, and the data space.

Problem Determination:

- 1. Analyze the ICHRST00 dump as described.
- 2. Use standard debugging methods to analyze this dump. To look at a data space with IPCS, you must know the name of the data space. The name of a data space obtained for RACLIST purposes is "IRRxxxxx" where xxxxx is a hex number. The name of the data space in the dump can be obtained by an IPCS command, "listdump select". Simply scan the command's output for "DSPNAME" and use the resulting name and ASID to access the data space.

RACF subsystem failures (IRRSSC01, IRRSSS01, and IRRLOG00)

All dumps issued by the RACF subsystem have the form:

DUMP_TITLE=uuuu subsystem,vvvvvvv task,www yyyyy module,zzzzzz segment.

The appropriate subsystem name, task name, abend code, module name, and segment name are all provided. The numbers following the module name give the compile date for that module.

SVC dump descriptions

An example of a RACF subsystem dump title is:

DUMP TITLE=RACF Subsystem, IRRSSC00 task, 0C1 abend, IRRSSM04 92100 module, WAITECB segment.

Component:

RACF (5752-XXH00)

Issuing Modules:

IRRSSC01 IRRSSS01

Explanation:

The RACF subsystem has issued dumps.

Problem Determination:

- 1. See z/OS MVS System Codes for an explanation of the abend code and the messages.
- 2. If the explanations in *z/OS MVS System Codes* do not help you solve the problem, see Abend troubleshooting table for instructions on debugging the problem.
- 3. When the dump title identifies IRRLOG00 as the failing CSECT, there may be additional diagnostic information available in the SYSOUT and CEEDUMP DDs for the subsystem started task.

Persistent verification failures

Dumps issued by RACF for persistent verification support in RACF's subsystem have the form:

DUMP TITLE=COMPON=RACF,COMPID=5752XXH00,ISSUER=IRRSGN06, MODULE=mmmmmmm,ABEND=S0xxx,REASON=yyyyyyyy

Component:

RACF (5752-XXH00)

Issuing Module:

mmmmmmmm

Explanation:

The RACROUTE REQ=SIGNON service has issued a dump.

Problem Determination:

- 1. Look up the abend and reason code in z/OS Security Server RACF Messages and Codes.
- 2. Use standard debugging methods to analyze the dump.

RACF I/O failures

Dumps issued by the RACF manager when an I/O occurs while processing a RACHECK, RACINIT, RACDEF, or RACF command request have the form:

DUMP TITLE= ISSUER=IRRMER01-RACF SVCS, I/O ERROR, SVC=*xxxxxxxxxx*, USER=yyyyyyyy ,GROUP=zzzzzzzz

where:

is the SVC name XXXXXXXX

is the RACF user's name from the ACEE or job name. *yyyyyyy*

is the RACF user's group name from the ACEE or step name. 7777777

An example of a RACF I/O dump title is:

DUMP TITLE= ISSUER=IRRMER01-RACF SVCS, I/O ERROR, SVC=ICHRSV00, USER=IBMUSER ,GROUP=SYS1

Component:

RACF (5752-XXH00)

Issuing Modules:

IRRMER01

Explanation:

An I/O error occurred and RACF issued an Sdump.

RACF index block error

In some cases where message IRR407I is issued, a DAE suppressible dump might be provided as a problem determination aid. This can occur during SVC 132 processing.

DUMP TITLE=COMPON=RACF,COMPID=5752XXH00,ISSUER=ICHRSV00, MODULE=IRRMLO00,MANAGER RC=4C,RBA=xxxxxxxxxxxxxx

where:

XXXXXXXXXXX is the RBA of the index block (which is not valid)

that produced message IRR407I.

An example of a RACF Index Block error dump title is:

DUMP TITLE=COMPON=RACF.COMPID=5752XXH00.ISSUER=ICHRSV00. MODULE=IRRML000, MANAGER RC=4C, RBA=00000001000

Component:

RACF (5752-XXH00)

Issuina Modules:

ICHRSV00

Explanation:

ICHRSV00 takes a DAE suppressible dump in cases where the RACF manager detects an index block that is not valid. In some cases this error occurs because of storage overlay. This dump captures information that might be helpful in debugging the overlay. IRRMLO00 is the RACF manager routine that determines whether conditions exist that call for this dump to be taken.

Dump title description for Callable Services

The following dump title is displayed on the MVS console when a RACF module used for processing a SAF callable service abends:

DUMP_TITLE=ISSUER=csect,COMPID=5752-XXH00,COMPON=RACF,CSECT=aaaaaaaaa, LVL=bbbbbbbbbb,ABEND=ssssrrr, USR=ccccccc

Where:

is the name of the csect that issued the dump, either IRRRCOMR csect

or IRRRCHD7

is the name of the RACF module that abended aaaaaaaa

bbbbbbbb is the product fmid (i.e. HRF7706)

Dump title description

is the system completion code (abend code), in hexadecimal SSS

is the reason code associated with the system completion code rrr

is the user's name from the RACF ACEE CCCCCCCC

When the module abends, the executing task is terminated. The areas dumped are RGN, SQA, TRT, and SUM.

Dump titles for the RACF/DB2 External Security Module

Restriction

This topic contains information about using RACF with DB2[®] Version 7, and earlier DB2 versions. For information about using RACF with DB2 Version 8, and later DB2 versions, see DB2 RACF Access Control Module Guide.

The RACF/DB2 external security module generates the following dump titles:

COMPON=RACF, COMPID=5752XXH00, ISSUER=DSNX@FRR, MODULE=IRR@XACS,

,L=zzzzzzzz ABEND=S0sss, REASON=NONE

COMPON=RACF, COMPID=5752XXH00, ISSUER=DSNX@FRR, MODULE=IRR@XACS, ABEND=S0sss, REASON=aaaaaaaaa, L=zzzzzzzz

COMPON=RACF, COMPID=5752XXH00, ISSUER=DSNX@FRR, MODULE=IRR@XACS, ABEND=Uuuuu, REASON=NONE ,L=ZZZZZZZZ

COMPON=RACF, COMPID=5752XXH00, ISSUER=DSNX@FRR, MODULE=IRR@XACS, ABEND=Uuuuu, REASON=aaaaaaaaa, L=zzzzzzzz

where:

SSS is the system abend code is the user abend code uuuu

aaaaaaaa is the abend reason code

ZZZZZZZZ is the module length

RACF/DB2 External Security Module diagnostic information

The RACF/DB2 external security module returns a parameter, XAPLDIAG, that DB2 and other program products can use to trap and obtain diagnostic information. When the RACF/DB2 external security module issues a RACROUTE REQUEST=FASTAUTH check that fails to grant access, the module records the failing SAF return code, RACF return code, and RACF reason code in XAPLDIAG. Each invocation of the RACF/DB2 external security module can issue multiple RACROUTE REQUEST=FASTAUTH macros, but the module can return only a single return code. However, the DB2 V8 external security module can store up to 20 sets of return codes from failing RACROUTE REQUEST=FASTAUTH macros in XAPLDIAG, allowing the results of a specific RACROUTE REQUEST=FASTAUTH macro to be determined.

Notes:

- 1. z/OS V1R5 supports DB2 V6, V7, and V8, but DB2 V6 and V7 have storage capacity for only 10 sets of return codes from failing RACROUTE REQUEST=FASTAUTH macros in XAPLDIAG.
- 2. The RACF/DB2 external security module for DB2 V8 is shipped by DB2.

RACF/DB2 diagnostic information

The XAPL parameter list can be captured using DB2 trace record IFCID 314. In addition, the return code and corresponding reason code (EXPLRC1 and EXPLRC2) for authorization failures are captured in DB2 trace record IFCID 140. The DB2 trace facility is documented in DB2 Administration Guide, SC26-8957.

The content of XAPLDIAG depends on the return code and reason code from the RACF/DB2 external security module.

- If EXPLRC1=4 and ECPLRC2=14 (decimal), the ALESERV failed and the module made no RACROUTE REQUEST=FASTAUTH checks. In this case the first word of XAPLDIAG contains the non-zero ALESERV return code.
- Otherwise, each word of XAPLDIAG can contain a SAF return code, RACF return code, and RACF reason code corresponding to a non-zero return code from a RACROUTE REQUEST=FASTAUTH macro. Information related to non-zero return codes is stored in XAPLDIAG beginning with the first word until information related to all non-zero return codes has been stored, or until the XAPLDIAG area has filled. XAPLDIAG contains 20 words, allowing information related to 20 FASTAUTH requests to be stored for an invocation of the RACF/DB2 external security module. If more than 20 FASTAUTH requests are issued, only the first 20 sets of return codes are stored.

Starting with DB2 Version 7, DBADM authorization checking for the CREATE VIEW privilege may result in more than 10 FASTAUTH requests, because a CREATE VIEW request may reference tables, or a combination of tables and views, from multiple databases. DB2 Version 7 passes the names of all the databases referenced in the CREATE VIEW using a database list pointed to by XAPLREL2. If SYSCTRL or SYSADM authorization checking does not grant the CREATE VIEW privilege and the XAPLCRVW field indicates that DBACRVW is enabled, the RACF/DB2 external security module checks the user's DBADM authorization for each database in the list. The result of each DBADM check is placed in the XAPLDBDA field associated with each database. The RACF/DB2 external security module updates XAPLDBDA with the following codes:

- Υ Access to the database is allowed.
- Ν Access to the database is not allowed.
- U RACF was unable to return a decision. This occurs when the FASTAUTH request returns a SAF return code of X'04'.

Although DBADM checks may be done for multiple databases, only the results of the first 20 FASTAUTH requests are stored in XAPLDIAG. The results of all DBADM checking for each database is contained in the XAPL parameter list and is available using DB2 trace record IFCID 314.

The RACF/DB2 external security module truncates the SAF return codes and RACF return codes to one byte, and the RACF reason code to two bytes, before storing them in XAPLDIAG. The format of each word in XAPLDIAG is:

XXYYZZZZ

where:

is the SAF return code XXis the RACF return code VV7777 is the RACF reason code

For a list of the RACF return codes and reason codes and their meanings, see z/OS Security Server RACF System Programmer's Guide.

For additional information on common problems that can occur as a result of adding installation-defined classes to the class descriptor table (CDT) for DB2 objects, see *z/OS Security Server RACF Security Administrator's Guide*.

VRA keys provided by RACF for some abends

For some abends, RACF provides VRA (variable recording area) keys that can help in describing a problem to the IBM support center or in narrowing a search when an initial search gets too many matches.

The VRA is part of the SDWA (system diagnostic work area) that recovery routines can use when a problem occurs. The VRA can be included in a SYS1.LOGREC record and in a system dump. To format the VRA, use the DAEDATA control statement in PRDMP or the DAEDATA verbexit in IPCS. Symptoms included in the VRA can be formatted using the SYMPTOMS control statement in PRDMP or the SYMPTOMS verbexit in IPCS.




Figure 57. Sample Symptoms for RACF (DAEDATA Output). This figure includes the RETAIN® search argument and the VRA keys as formatted by DAEDATA.

A number of headers for VRA keys are produced by RACF. These headers (labeled HEADER FOR DATA) describe error data (labeled HEX ERROR DATA). For example, in this dump RACFCNTS is the header for 01000000, and IPLPTR is the header for 0000EB74.

Headers	Descr	Description		
RACFCNTS	Number of the current RACF macro request on which the RACF manager failed. This number can be interpreted as X'wwxxyyzz', where:			
	WW	is the number of the IPL being processed		
	XX	is the number of the action being processed		
	уу	is the number of the test being processed		
	ZZ	is reserved		
IPLPTR		er to the input parameter list for the current RACF ger request.		

ACTNPTR Pointer to the action being performed at the time of the

abend.

TESTPTR Pointer to the test being performed at the time of the

abend.

MGRREQST RACF manager request ID for the ICHEINTY macro being

performed at the time of the abend. This request ID is also reported in message ICH413I. This ID is included only on

internal RACF requests.






Figure 58. Sample SDWA for RACF





2 HEX ERROR DATA



Front-ending RACF commands

The RACF common command exit, IRREVX01, allows customers to customize or cancel RACF commands before the RACF command processor is invoked. This exit is the recommended vehicle for preprocessing RACF commands. Before RACF provided this exit, some customers created their own front-end processors to preprocess RACF commands. Because RACF 2.2 changed the way RACF processes commands, customers who wrote front-end processors before RACF 2.2 and who want to continue to use these front-end processors might have to change them. This information is intended for those customers.

Note: If you currently use a front-end processor for commands, it is recommended that you replace it with an IRREVX01 exit.

Command processing changes

Before RACF 2.2, when a RACF TSO command was issued, control was passed directly to the appropriate command processor.

To make this happen, RACF included an entry similar to the following for ADDGROUP in the linkage editor statements for each RACF command.

```
INCLUDE AOSBN(ICHCAG00)
INCLUDE AOSBN(other modules)
ALIAS AG, ADDGROUP
ENTRY ICHCAG00
SETCODE AC(1)
NAME ICHCAGOO(R)
```

Note: AG or ADDGROUP is the alias name by which the command is issued by a user and ICHCAG00 is the full name of the command by which it is invoked internally.

In RACF 2.2 and OS/390 Security Server (RACF), the entry in the linkage editor statements for most RACF commands look like this:

```
INCLUDE AOSBN(ICHCAG00)
INCLUDE AOSBN(other modules)
ENTRY ICHCAG00
NAME ICHCAGOO(R)
```

Note: The aliases are not present.

The aliases have been removed from each individual command and placed in a new entry for IRRENV00.

```
INCLUDE AOSBN(IRRENVOO)
INCLUDE AOSBN(other modules)
ENTRY IRRENVOO
ALIAS AD, ADDSD
ALIAS AG, ADDGROUP
ALIAS other commands
SETCODE AC(1)
NAME IRRENVOO(R)
etc.
```

IRRENV00 receives control before each command processor. If the AT or ONLYAT keywords were not specified, IRRENV00 invokes the appropriate command processor using its full name. When the command processor returns control, IRRENV00 determines if automatic direction is required for the command. If so, a work item is sent to the RACF subsystem address space. If the AT or ONLYAT keywords were specified, IRRENV00 sends the command to the RACF subsystem address space for processing.

Considerations if writing a command front-end processor

If IRRENV00 processing is bypassed by a front-end processor, RACF remote sharing functions (RRSF) will not work. When writing a command front-end processor, ensure IRRENV00 gets control somewhere in the processing before the command processor.

To ensure that all RRSF functions will be processed as specified, commands must be invoked by one of the alias names with which they are shipped (for example, AG, ADDGROUP, ADDSD, and so on). When IRRENV00 receives control, the command buffer must have one of the two alias names in the first position. For example, AG or ADDGROUP should be coded, not ICHCAG00. If a front-end processor gets control prior to IRRENV00, set the command buffer correctly prior to attaching or linking to IRRENV00. If it gets control after IRRENV00, do not change the content of the command buffer as doing so may result in the information not being processed correctly by automatic command direction.

If the alias is changed to point to a front-end processor, it gets control prior to IRRENV00 when a command is issued as a TSO command. However, the preprocessor does not get control in all situations. For example, it does not get control for commands resulting from automatic command direction, or for commands issued from the RACF parameter library.

One possible approach to avoid the pitfalls mentioned is to include your front-end processor in RACF's load module.

INCLUDE mylib(mymod) INCLUDE SYSLMOD (ICHCAG00) ENTRY mymod NAME ICHCAGOO(R)

After completing its processing, the front-end processor will need to call the entry point for RACF's command processor. If the front-end processor needs to communicate with the user, be aware that the preprocessor could be running in the RACF subsystem address space and not in the TSO user's address space. The ACEERASP bit (x'40') is set in the ACEEFLG3 flag field of the ACEE for the RACF subsystem address space.

Assigning the entry point to the front-end processor (mymod) causes it to be invoked at the same point in the processing that the specific command processing would have been invoked by RACF. Because the alias is not included, the RACF remote sharing functions will operate and IRRENV00 will be invoked.

The DEBUG command

ı 1

1

The DEBUG command starts the diagnostic print statements that wrap the cryptographic library calls and displays additional diagnostic information for RACDCERT invoked ICHEINTY ALTER, RACROUTE REQUEST=EXTRACT, and RACROUTE REQUEST=DEFINE failures. However, the contents of these messages will not be documented in any publication. When a problem is encountered, customers can use this keyword to gather diagnostic information for the IBM Support Center.

Chapter 7. Error recovery for RACF sysplex data sharing

This topic describes actions to take in order to allow RACF to continue servicing requests when you encounter a situation where coupling facility recovery scenarios do not work properly.

Actions to recover from a coupling facility error

If you encounter a situation where coupling facility recovery scenarios do not work properly, the following information might make it possible for RACF to continue servicing requests.

For example, we assume a sysplex with 3 members: J90, J91, and J92. A coupling facility containing RACF Structure IRRXCF00_B001 has been lost. Member J90 remains active.

The following messages are received at the operator console:

IRRX016I RACF MEMBER J90 DETECTED A COUPLING FACILITY ERROR IXC521I REBUILD FOR STRUCTURE IRRXCF00_B001 HAS BEEN STARTED IRRX020I REBUILD FOR STRUCTURE IRRXCF00_B001 ON MEMBER J90 HAS BEEN INITIATED

The following message is not received at the operator console:

IRRX008I REBUILD FOR STRUCTURE IRRXCF00 B001 HAS BEEN COMPLETED

Issuing the following command from the operator console:

DISPLAY XCF, STRUCTURE

displays the following: IRRXCF00 B001 ALLOCATED REBUILDING

Issuing the following command from the operator console:

DISPLAY GRS, CONTENTION

displays the following: SYSZRAC2 , minor name backup-racf-db is held on system J90 by RACFDS

In this situation, members of the sysplex might be unable to function properly because RACF is holding enqs. A rebuild of a RACF structure has been requested but cannot go ahead. The following steps might be helpful in allowing RACF to continue operating, though it will be at a degraded mode.

- 1. Make sure if message IXC402D has been received one or more times at the operator's console, you reply "down" to all of them. If this allows REBUILD to complete, you do not need to continue with the following steps.
- 2. Issue the following command at the operator console:

SETXCF STOP, REBUILD, STRNAME=IRRXCF00 B001

This command stops REBUILD and release enqs. Additionally, message IRRX004I is received, which displays the following: IRRX004I MEMBER J90 IS IN READ-ONLY MODE.

3. Issue the following command at the operator console:

RVARY NODATASHARE

All remaining sysplex members now operate off of the database, without the coupling facility. Note that performance will not be as good while running without the coupling facility.

4. You might be able to further improve the situation if you have configured your sysplex appropriately. This means that you have more than one coupling facility and that after the failure of one of them is still available. To illustrate this, read the following:

Take, for example, two coupling facilities. All structures for the primary RACF database are assigned to one coupling facility and all structures for the backup RACF database are assigned to the other coupling facility. (In this example, assume that no alternate coupling facilities have been assigned.) If you lose one or the other of the coupling facilities in this configuration, you can still get back into data sharing mode, though it will be without a backup database.

For example:

 If the coupling facility containing the primary database structures goes down, issue the command:

RVARY SWITCH

which makes the backup database primary and deactivates the old primary

 If the coupling facility containing the backup database structures goes down, issue the command:

RVARY INACTIVE

on the backup database.

· Issue the command:

RVARY DATASHARE

which allows remaining sysplex members the ability to connect to all structures on the available coupling facility.

The fourth step has an adverse consequence, however, Although these steps improve performance while a coupling facility is unavailable, your backup and primary databases will most likely become out of synch. This will need to be resolved before you can go back to normal operations with both primary and backup databases. This can be done by using IRRUT200, as documented in z/OS Security Server RACF System Programmer's Guide.

Appendix A. The Inventory Control Block (ICB)

The ICB is included here to help you diagnose RACF problems.

Common Name: RACF Database Inventory Control Block

Macro ID:ICHPICBDSECT Name:INVICB

Owning Component: Resource Access Control Facility (XXH00)

Eye-Catcher ID: RACFICB
Offset: 1010
Length: 8

Storage Attributes:

Subpool: 231
Key: 0
Residency: ECSA

Size: 4096 bytes

Created by: IRRMIN00 or IRRUT400 on the RACF database. In storage by RACF initialization when

the system is in data sharing mode or if the database is not shared.

Pointed to by: DSDEHDR in the DSDT data area

Serialization: For the copy on the data set: SYSZRACF RESERVE or SYSZRACF ENQ

For the in-storage copy: SYSZRACF ENQ

Function: The ICB is the first record of the RACF database. It provides a control area for the

routines that manage RACF data. This control area contains information needed to

locate data related to the templates.

Offset	Offset				
(Dec)	(Hex)	Туре	Len	Name (Dim)	Description
0	(0)	STRUCTURE	4096	INVICB	Inventory Control Block
0	(0)	CHARACTER	2599	ICBHDR	
0	(0)	ADDRESS	4	ICBCHAIN	Reserved
4	(4)	SIGNED	4	ICBBAMNO	Number of BAM blocks in data set
8	(8)	BITSTRING	6	ICCIBRBA	RBA of highest level CIB
14	(E)	BITSTRING	6	ICISSRBA	RBA of first block of index sequence set
20	(14)	BITSTRING	6	ICBAMRBA	RBA of first BAM
26	(1A)	BITSTRING	1	ICBFLAGS	Status
		1		ICBEXTND	RACF data set has been extended, RACF will no longer process updates to this version
		.1		*	Reserved, do not use
		1		ICBEDAT	RESIDENT data blocks option used on some system
		1		ICBDSFMT	1 = new RACF data set format
		1		ICBWIP	HPCS 1 = Write In Progress
		111		*	Reserved
27	(1B)	ADDRESS	1	ICTMPCNT	Number of templates
28	(1C)	BITSTRING	6	ICBAMHWM	BAM HWM.
34	(22)	CHARACTER	16	ICBTEMP (9)	Space for 9 template DEFNS
34	(22)	SIGNED	2	ICTMPL	Template length
36	(24)	ADDRESS	1	ICTMPN	Template number
37	(25)	BITSTRING	1	ICTMRSV1	Align to half word boundary
38	(26)	BITSTRING	6	ICTMPRBA	RBA of FDT
44	(2C)	CHARACTER	6	ICTMRSV2	Reserved
178	(B2)	CHARACTER	16	*	Reserved
194	(C2)	CHARACTER	1	ICBSTAT	Status

Offset	Offset				
(Dec)	(Hex)		Len	Name (Dim)	Description
		1		*	Reserved, do not use. Maps the 'RCVTRNA' flag
		.1		ICBNLS	Bypass RACINIT statistics
		1		ICBNDSS	Bypass data set statistics
		1		ICBNTVS	No tape volume statistics
		1		ICBNDVS	No direct access volume statistics
		1		ICBNTMS	No terminal statistics
		1.		ICBNADS	No ADSP protection
		1		ICBEGN	EGN support in effect
195	(C3)	BITSTRING	1	ICBEXTA	Reserved
196	(C4)	CHARACTER	1	ICBSTAT1	
		1		ICBTAPE	Tape volume protection
		.1		ICBDASD	DASD volume protection
		1		ICBDGEN	Generic profiles for dataset class
		1		ICBDGCM	Generic commands for dataset class
		1		ICBRDSN	Input data set name will be used for logging and messages
		1		ICBJXAL	JES-XBMALLRACF is in effect
		1.		ICBJCHK	JES-EARLYVERIFY is in effect
		1		ICBJALL	JES-BATCHALLRACF is in effect
197	(C5)	CHARACTER	1	ICBAUOP	RACF audit options
		1		*	Reserved
		.1		ICBAGRO	Audit GROUP class
		1		ICBAUSE	Audit USER class
		1		ICBADAT	Audit DATASET class
		1		ICBADAS	Audit TAREVOL class
		1		ICBATAP ICBATER	Audit TAPEVOL class Audit TERMINAL class
		1		ICBATER	Audit PERMINAL class Audit OPERATIONS attribute
198	(C6)	BITSTRING	1	ICBAXTA	Reserved
199		CHARACTER	1	ICBEROP	Miscellaneouse options
	(-)	1		ICBTERP	Terminal authorization checking
		.1		ICBTUAC	Default UACC for terminals not defined to
					RACF. If ON, UACC = NONE. If OFF, UACC = READ.
		1		ICBAVIO	Do not create log record for command
					violations only
		1		ICBSAUD	Do not audit SPECIAL users
		1		ICBMGDG	MODEL-GDG in effect
		1		ICBMUSR	MODEL-USER in effect
		1.		ICBMGRP	MODEL-GROUP in effect
	(00)	1		ICBLGRP	LIST-OF-GRPS in effect
200	(C8)	SIGNED	4	ICBCHCT (10)	Change count array for all levels of index blocks
240	(F0)	ADDRESS	1	ICBPINV	Global max password interval value, valid range 1-254
241	(F1)	BITSTRING	4	ICBCSTA	Class STATISTICS mask
245	. ,	BITSTRING	4	ICBCAUD	Class AUDIT mask
249	. ,	BITSTRING	4	ICBCPRO	Class PROTECTION mask
253	, ,	UNSIGNED	1	ICBPHIST	Password HISTORY value
254	. ,	UNSIGNED	1	ICBPRVOK	Password REVOKE value
255		UNSIGNED	1	ICBPWARN	Password WARNING value
256		CHARACTER	10	ICBPSYN (8)	Password SYNTAX rules
256	(100)	UNSIGNED	1	ICBPSLEN	Starting length value

Offset	Offset				
(Dec)	(Hex)		Len	Name (Dim)	Description
257	(101)	UNSIGNED	1	ICBPELEN	Ending length value
258	(102)	CHARACTER	8	ICBPRULS	Content rules
258	(102)	CHARACTER	1	ICBPRUL1	Content rule
259	(103)	CHARACTER	1	ICBPRUL2	Content rule
260	(104)	CHARACTER	1	ICBPRUL3	Content rule
261	(105)	CHARACTER	1	ICBPRUL4	Content rule
262	(106)	CHARACTER	1	ICBPRUL5	Content rule
263	(107)	CHARACTER	1	ICBPRUL6	Content rule
264	(108)	CHARACTER	1	ICBPRUL7	Content rule
265	(109)	CHARACTER	1	ICBPRUL8	Content rule
336	(150)	UNSIGNED	1	ICBINACT	INACTIVATE interval
337	(151)	BITSTRING	4	ICBCGEN	Generic profile checking, class mask
341	(155)	BITSTRING	4	ICBCGCM	Generic commansd processing, class mask
345	(159)	BITSTRING	4	ICBMOPT	Miscellaneous options
		1		ICBFPDS	Fastpath for DATASET class
		.1		ICBTDSN	Tape data set protection in effect
		11 1111		*	Reserved
		1		ICBPRO	PROTECT-ALL is in effect
		.1		ICBPROF	1 - PROTECT-ALL WARNING is in effect, 0 -
					PROTECT-ALL FAILURE is in effect (This flag
					os ognored if ICBPRO has a value of '0'B)
		1		ICBEOS	ERASE-ON-SCRATCH is in effect
		1		ICBEOSL	ERASE-ON-SCRATCH by SECLEVEL is in
					effect (This flag is ignored if ICBEOS has a
					value of '0'B)
		1		ICBEOSA	ERASE-ON-SCRATCH for all data sets is in
					effect (This flag is ignored if ICBEOS has a
		1		ICBPLC	value of '0' B)
		1		ICBPLC	Mixed case password Reserved
		11		ICBPROG	
		1		ICBPROG	PROGRAM CONTROL is in effect
		.111 1111		*	Reserved Reserved
347	(1ED)	1111 1111 DITETRING	4	*	Reserved
_	, ,	BITSTRING	1	ICDEDTU	
349 353	, ,	BITSTRING UNSIGNED	4 1	ICBFPTH ICBSLVL	Class FASTPATH mask Security Level for ERASE-ON-SCRATCH
	, ,				
354	, ,	UNSIGNED	2	ICBRETP	Security Retention Period
356	, ,	UNSIGNED	1	ICBQLLN	Length of prefix for single level data set names
357	(105)	CHARACTER	9	ICBQUAL	Installation controlled prefix for single level dataset names, plus period for level
266	(16E)	LINGIGNED	1	ICBSLAU	SECLEVEL to audit
366	(100)	UNSIGNED	ı	IUDOLAU	SECLEVEL IO AUGII

Offset	Offset				
(Dec) 367	(Hex)	Type UNSIGNED		Name (Dim) ICBALIAS	Description 367 (16F) UNSIGNED 1 ICBALIAS application identity mapping byte.
					4 stages:
					• 0=stage 0
					not active
					 only mapping profiles
					• 1=stage 1
					- active
					 maintain alias index, but also maintain and use VLF and mapping profiles
					Reject locates of application identities
					• 2=stage 2
					- active
					maintain and use alias index, but also
					maintain VLF the mapping profiles
					 Allow locates of application identities
					• 3=stage 3
					active
					 maintain and use only alias index
368	(170)	SIGNED	4	ICBCHCTD	mapping profiles have been removed Change count for data blocks, used to maintain current in-storage blocks with a shared RACF data set
372	(174)	CHARACTER	8	ICBSWPW	Password for RVARY SWITCH command
380	, ,	CHARACTER	8	ICBINPW	Password for RVARY ACTIVE/INACTIVE command
388	(184)	BITSTRING	16	ICBLRCL	CDT-ANCHORED RACLISTED profile class mask, ON if active
404	(194)	BITSTRING	16	ICBLGNL	CDT-ANCHORED GENLISTED profile class mask, ON if active
420	(1A4)	BITSTRING	16	ICBLSTAC	Class STATISTICS option mask long version, ON if active
436	(1B4)	BITSTRING	16	ICBLAUDC	Class AUDITING option mask long version, ON if active
452	(1C4)	BITSTRING	16	ICBLPROC	Class PROTECTION option mask long version, ON if active
468	(1D4)	BITSTRING	16	ICBLGENC	Class mask for GENERIC PROFILE CHECKING long version, ON if active
484	(1E4)	BITSTRING	16	ICBLGCMC	Class mask for GENERIC COMMAND CHECKING long version, ON if active
500	(1F4)	BITSTRING	16	ICBLFPTC	Class FASTPATH option mask long version, ON if active
516	(204)	SIGNED	1	ICBPMIN	SETROPTS PASSWORD(MINCHANGE) setting
517	, ,	ADDRESS	1	ICNTMPCT	Number of nre templates
518	, ,	CHARACTER	16	ICBTMPVR	Template version levels
518	, ,	CHARACTER	8	ICBTMPRL	Release level
526	. ,	CHARACTER	8	ICBTMPAL	APAR level
534		BITSTRING	6	ICBTXRBA	RBA of the template extensions
540 542	, ,	SIGNED	126	ICBTXLN *	Length of the template extension Reserved
542 678	. ,	CHARACTER BITSTRING	136 4	ICBVMSSP	VM 370 SYNC counter
070	(2710)	Dironning	-	IOD A IAIOOI	VIVI 070 OTTAO COUNTER

Offset	Offset				
(Dec)	(Hex)			Name (Dim)	Description
682	, ,	BITSTRING	4	ICBVMSXA	VMXA ACI SYNC counter
686	(2AE)	CHARACTER	8	ICBBMAPA	VM XA profile name which contains the audit settings
694	(2B6)	CHARACTER	8	ICBBMAPP	VM XA profile name contains the project settings
702	(2BE)	CHARACTER	92	ICBBMAP	Saved copy of the ACI bit map located in the CP nucleus
702	(2BE)	BITSTRING	2	ICBMAPSZ	Length of the entire ACI bit map with uncompressed events
704	(2C0)	BITSTRING	1	ICBDIAL	Indicator for: DIAL CMND
705	(2C1)	BITSTRING	1	ICBPRMSG	Indicator for: DIAL CMND, PRELOGON MESSAGE CMD
706	(2C2)	BITSTRING	88	ICBEVENT	ACI bit map events
794	(31A)	SIGNED	2	ICBSINT	LU Session Interval
796	(31C)	BITSTRING	16	ICBLGAL	SETROPTS "LOGOPTIONS ALWAYS" class mask, ON if active
812	(32C)	BITSTRING	16	ICBLNVR	SETROPTS "LOGOPTIONS NEVER" class mask, ON if active
828	(33C)	BITSTRING	16	ICBLGSU	SETROPTS "LOGOPTIONS SUCCESSES" class mask, ON if active
844	(34C)	BITSTRING	16	ICBLGFL	SETROPTS "LOGOPTIONS FAILURES" class mask, ON if active
860	(35C)	CHARACTER	8	ICBJSYS	User ID from the SETROPTS command JES(NJEUSERID(<i>id</i>))
868	(364)	CHARACTER	8	ICBJUND	User ID from the SETROPTS command JES(UNDEFINEDUSER(id))
876	(36C)	SIGNED	4	ICBRCGSN	RACF group data synchronization value
880	(370)	BITSTRING	1	ICBLOGD	LOGOPTIONS for DATASET
		1		ICBDLGA	LOGOPTIONS "ALWAYS" for the DATASET class
		.1		ICBDLGN	LOGOPTIONS "NEVER" FOR THE DATASET CLASS
		1		ICBDLGS	LOGOPTIONS "SUCCESSES" for the DATASET class
		1		ICBDLGF	LOGOPTIONS "FAILURES" for the DATASET class
		1111		*	Reserved
881	(371)	BITSTRING	1	ICBFLG2X	RACF SETROPTS options
		1		ICBCMPM	SETROPTS COMPATMODE, ON if active
		.1		ICBMLSF	SETROPTS MLS FAILURES/WARNING - FAILURES if "ON" - (1) - WARNING if "OFF" -
		1		ICBMLAF	(0) SETROPTS MLACTIVE FAILURES/WARNING - FAILURES if "ON" - (1) - WARNING if "OFF" - (0)
		1		ICBCATF	SETROPTS CATDSNS FAILURES/WARNING - FAILURES if "ON" - (1) - WARNING if "OFF" - (0)
		1		ICBAAPL ICBNOADC	SETROPTS APPLAUDIT ON if active SETROPTS NOADDCREATOR - on if
					NOADDCREATOR in effect
		11		*	Reserved
882	(372)	CHARACTER	8	ICBSPAUD	VM/SP profile names which contains the audit settings

Offset	Offset	_			
(Dec) 890	(Hex) (37A)	Type CHARACTER	Len 8	Name (Dim) ICBSPCTL	Description VM/SP profile names which contains the
	()				protect settings
898	(382)	BITSTRING	1	ICBFLG2 ICBSLCL	RACF 1.9.0 SETROPTS options SETROPTS SECLABELCONTROL - ON if active
		.1		ICBCATD	SETROPTS CATDSNS - ON if active
		1		ICBMLQT	SETROPTS MLQUIET - ON if active
		1		ICBMLST	SETROPTS MLSTABLE - ON if active
		1		ICBMLS	SETROPTS MLS - ON if active
		1		ICBMLAC	SETROPTS MLACTIVE - ON if active
		1.		ICBGNOW	SETROPTS GENERICOWNER - ON if active
899	(383)	1 CHARACTER	3	ICBAUSL ICBNL1	SETROPTS SECLABELAUDIT - ON if active PRIMARY LANGUAGE default
902	, ,	CHARACTER	3	ICBNL2	SECONDARY LANGUAGE default
905	. ,	BITSTRING	1	ICBDIRT	Dirty bits to indicate whether fields have been
	, ,				initialized.
		1		ICBSESS	SESSIONINTERVAL dirty bit, 0=>Field not
				*	initialized, 1=>Field is initialized.
006	(OO A)	.111 1111	4	iCBML2F	Reserved
906	(36A)	BITSTRING	1		SETROPTS options for RACF z/OS multilevel security support
		1		ICBMLFS	Security labels required for File System Objects
					Objects
					SETR MLFSOBJ
		.1		ICBMLIP	Security labels required for IPC Objects
					SETR MLIPCOBJ
		1		ICBMLNM	Display of Names Restricted by Security label
		1		IODODYO	SETR MLNAMES
		1		ICBSBYS	Security label by System requested
					SETR SECLBYSYSETM
		1111		*	Reserved
907	(38B)	CHARACTER	85	*	Reserved
992		CHARACTER	6	ICBALRBA	Highest ALIAS index block
998	, ,	CHARACTER	6	ICBASRBA	ALIAS index sequence set
1004	(3EC)	ADDRESS	4	ICBSMCT	Count field to control purge of VLF class IRRSMAP
1008	(3E0)	CHARACTER	1	ICBKRBLV	SETROPTS KERBLVL setting
1009		CHARACTER	1	*	Reserved
1010	. ,	CHARACTER	8	ICBID	Identifier, gets filled in during IRRMIN00
	(-)				initialization
1018	(3FA)	CHARACTER	6	ICBVRMN	Version/release/ modification number, also filled in IRRMIN00
					End of first 1024 bytes
					·
1024		SIGNED	2	ICTSEGLN	Length of segment table
1026		BITSTRING	6	ICTSEGRB	RBA of segment table
1032	(408)	BITSTRING	1	ICBRDSFL	RDS flags
		1		ICBINITF	ICB was completely initialized by RDS IRRMIN00
		.111 1111		*	Reserved
1033	(409)	CHARACTER	3	*	Reserved; Prevent byte skip msg

Offset	Offset				
(Dec)	(Hex)	Туре	Len	Name (Dim)	Description
1036	(40C)	UNSIGNED	4	ICBUSCT	ACEE data repository change count for user profile
1040	(410)	UNSIGNED	4	ICBGPCT	ACEE data repository change count for group profile
1044	(414)	UNSIGNED	4	ICBGRCT	ACEE data repository change count for general resource classes APPL, APPCPORT, JESINPUT, CONSOLE, TERMINAL, GTERMINL & SECLABEL
1048	(418)	ADDRESS	4	ICBUMCT	count field to control purge of VLF class IRRUMAP
1052	(41C)	ADDRESS	4	ICBGMCT	count field to control purge pf VLF class IRRGMAP
1056	(420)	CHARACTER	7	ICBTMPLV	Template level value filled in by IRRMIN00.
1063	(427)	BITSTRING	128	ICBVPROC	Class protection mask
1191	(4A7)	BITSTRING	128	ICBVGENC	Generic profile checking class mask
1319	(527)	BITSTRING	128	ICBVGCMC	Generic command processing class mask
1447	(5A7)	BITSTRING	128	ICBVRCL	CDT-anchored RACLISTed profile class mask
1575	(627)	BITSTRING	128	ICBVGNL	CDT-anchored GENLISTed profile class mask
1703	(6A7)	BITSTRING	128	ICBVFPTC	Fastpath option class mask
1831	(727)	BITSTRING	128	ICBVAUDC	Auditing option class mask
1959	(7A7)	BITSTRING	128	ICBVSTAC	Statistics option mask
2087	(827)	BITSTRING	128	ICBVLGA	SETROPTS LOGOPTIONS ALWAYS class mask
2215	(8A7)	BITSTRING	128	ICBVLNV	SETROPTS LOGOPTIONS NEVER class mask
2343	(927)	BITSTRING	128	ICBVLGS	SETROPTS LOGOPTIONS SUCCESSES class mask
2471	(9A7)	BITSTRING	128	ICBVLGF	SETROPTS LOGOPTIONS FAILURES class mask
2599	(A27)	ADDRESS	1	ICTMPXCT	Number of template extensions
2600	(A28)	CHARACTER	1496	ICBRSVD	RESERVED

End of ICB mapping

Constants

Len	Туре	Value	Name	Description
8	CHARACTER	RACFICB	ICBIDC	Constant for ICBID field
6	CHARACTER	1090	ICB1090	Constant representing FMID HRF1902 for ICBVRMN field
6	CHARACTER	1092	ICB1092	Constant representing FMID JRF1922 for ICBVRMN field
6	CHARACTER	2010	ICB2010	Constant representing FMID HRF2210 for ICBVRMN field
6	CHARACTER	2020	ICB2020	Constant representing FMID HRF2220 for ICBVRMN field
6	CHARACTER	2030	ICB2030	Constant representing FMID HRF2230 for ICBVRMN field
6	CHARACTER	2040	ICB2040	Constant representing FMID HRF2240 for ICBVRMN field
6	CHARACTER	2060	ICB2060	Constant representing FMID HRF2260 for ICBVRMN field
6	CHARACTER	2608	ICB2608	Constant representing HRF2608 for ICBVRMN field

Len	Туре	Value	Name	Description
6	CHARACTER	7703	ICB7703	Constant representing HRF7703 for ICBVRMN field
6	CHARACTER	7705	ICB7705	Constant representing HRF7705 for ICBVRMN field
6	CHARACTER	7706	ICB7706	Constant representing HRF7706 for ICBVRMN field
6	CHARACTER	7707	ICB7707	Constant representing HRF7707 for ICBVRMN field
6	CHARACTER	7708	ICB7708	Constant representing HRF7708 for ICBVRMN field
6	CHARACTER	7709	ICB7709	Constant representing HRF7709 for ICBVRMN field
6	CHARACTER	7720	ICB7720	Constant representing HRF7720 for ICBVRMN field
6	CHARACTER	7730	ICB7730	Constant representing HRF7730 for ICBVRMN field
6	CHARACTER	7740	ICB7740	Constant representing HRF7740 for ICBVRMN field
l 6	CHARACTER	7750	ICB7750	Constant representing HRF7750 for ICBVRMN field

Cross Reference

	Hex	Hex	
Name	Offset	Value	Level
ICBAAPL	371	08	4
ICBADAS	C5	08	4
ICBADAT	C5	10	4
ICBAGRO	C5	40	4
ICBALIAS	16F		3
ICBALRBA	3E0		3
ICBAMHWM	1C		3
ICBAMRBA	14		3
ICBAOPR	C5	01	4
ICBASRBA	3E6		3
ICBATAP	C5	04	4
ICBATER	C5	02	4
ICBAUOP	C5		3
ICBAUSE	C5	20	4
ICBAUSL	382	01	4
ICBAVIO	C7	20	4
ICBAXTA	C6		3
ICBBAMNO	4		3
ICBBMAP	2BE		3
ICBBMAPA	2AE		3
ICBBMAPP	2B6		3
ICBCATD	382	40	4
ICBCATF	371	10	4
ICBCAUD	F5		3
ICBCGCM	155		3
ICBCGEN	151		3
ICBCHAIN	0		3
ICBCHCT	C8		3
ICBCHCTD	170		3

	Hex	Hex	
Name	Offset	Value	Level
ICBCMPM	371	80	4
ICBCPRO	F9		3
ICBCSTA	F1		3
ICBDASD	C4	40	4
ICBDGCM	C4	10	4
ICBDGEN	C4	20	4
ICBDIAL	2C0		4
ICBDIRT	89		3
ICBDLGA	370	80	4
ICBDLGF	370	10	4
ICBDLGN	370	40	4
ICBDLGS	370	20	4
ICBDSFMT	1A	10	4
ICBEDAT	1A	20	4
ICBEGN	C2	01	4
ICBEOS	15A	20	4
ICBEOSA	15A	08	4
ICBEOSL	15A	10	4
ICBEROP	C7	. •	3
ICBEVENT	2C2		4
ICBEXTA	C3		3
ICBEXTND	1A	80	4
ICBFLAGS	1A		3
ICBFLG2	382		3
ICBFLG2X	371		3
ICBFPDS	159	80	4
ICBFPTH	15D		3
ICBGMCT	41C		3
ICBGNOW	382	02	4
ICBGPCT	410	V -	3
ICBGRCT	414		3
ICBHDR	0		2
ICBID	3F2		3
ICBINACT	150		3
ICBINITF	408	80	4
ICBINPW	17C		3
ICBJALL	C4	01	4
ICBJCHK	C4	02	4
ICBJSYS	35C		3
ICBJUND	364		3
ICBJXAL	C4	04	4
ICBKRBLV	3F0		3
ICBLAUDC	1B4		3
ICBLFPTC	1F4		3
ICBLGAL	31C		3
ICBLGCMC	1E4		3
ICBLGENC	1D4		3
ICBLGFL	34C		3
ICBLGNL	194		3
ICBLGRP	C7	01	4
ICBLGSU	33C	-	3
ICBLNVR	32C		3
ICBLOGD	370		3
.022302	J. 0		-

Name		Hex	Hex	
ICBLRCL	Name	Offset	Value	Level
ICBLSTAC	ICBLPROC	1C4		3
ICBMAPSZ	ICBLRCL	184		3
ICBMGDG				3
ICBMGRP				4
ICBMLAC 382			08	4
ICBMLAF	ICBMGRP	C7	02	4
ICBMLFS	ICBMLAC	382	04	4
ICBMLIP			20	4
ICBMLNM	ICBMLFS	38A	80	4
ICBMLQT	ICBMLIP	38A	40	4
ICBMLS	ICBMLNM	38A	20	4
ICBMLSF	ICBMLQT	382	20	4
ICBMLST	ICBMLS	382	08	4
ICBML2F	ICBMLSF		40	4
ICBMOPT	ICBMLST		10	
ICBMUSR				
ICBNADS				3
ICBNDSS				
ICBNDVS				
ICBNLS			20	4
ICBNL1				4
ICBNL2			40	
ICBNOADC 371 04 4 ICBNTEMP 206 3 ICBNTMS C2 04 4 ICBNTVS C2 10 4 ICBPELEN 101 4 ICBPHIST FD 3 ICBPHIST FD 3 ICBPRIV FO 3 ICBPRIV FO 3 ICBPRING 2C1 4 ICBPROG 15A 80 4 ICBPROG 15A 40 4 ICBPRULS 102 4 ICBPRULS 102 4 ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUB 109 5 ICBPRUB 109 5 ICBPRUB 100 4 ICBPSYN 100 3 ICBPWARN FF 3 </td <td></td> <td></td> <td></td> <td></td>				
ICBNTEMP 206				
ICBNTMS C2 04 4 ICBNTVS C2 10 4 ICBPELEN 101 4 ICBPHIST FD 3 ICBPINV F0 3 ICBPRMSG 2C1 4 ICBPRMSG 2C1 4 ICBPRO 15A 80 4 ICBPROF 15A 40 4 ICBPROG 15B 80 4 ICBPRULS 102 4 1 ICBPRULS 102 5 1 ICBPRUL1 102 5 1 ICBPRUL2 103 5 1 ICBPRUL3 104 5 5 ICBPRUL4 105 5 5 ICBPRUL5 106 5 5 ICBPRUL6 107 5 5 ICBPRUL8 109 5 5 ICBPRUL8 109 5 6 ICBPSULN 100 <		371	04	
ICBNTVS C2 10 4 ICBPELEN 101 4 ICBPHIST FD 3 ICBPINV F0 3 ICBPRMSG 2C1 4 ICBPRO 15A 80 4 ICBPROF 15A 40 4 ICBPROG 15B 80 4 ICBPRULS 102 4 6 ICBPRULS 102 5 6 ICBPRUL2 103 5 6 ICBPRUL3 104 5 6 ICBPRUL4 105 5 6 ICBPRUL5 106 5 6 ICBPRUL6 107 5 5 ICBPRUL8 109 5 6 ICBPRVOK FE 3 1 ICBPSYN 100 4 4 ICBPSYN 100 3 1 ICBQULN 164 3 1 ICBROSN 36C				
ICBPELEN				
ICBPHIST FD 3 ICBPINV F0 3 ICBPRMSG 2C1 4 ICBPRO 15A 80 4 ICBPROF 15A 40 4 ICBPROG 15B 80 4 ICBPRULS 102 4 ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL8 109 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQUAL 165 3 ICBROSSN 36C 3 ICBRDSFL 408 3			10	4
ICBPINV F0 3 ICBPRMSG 2C1 4 ICBPRO 15A 80 4 ICBPROF 15A 40 4 ICBPROG 15B 80 4 ICBPRULS 102 4 ICBPRULS 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRUL8 109 5 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPSYN 100 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBROSN 36C 3 ICBRDSFL 408 3	ICBPELEN			
ICBPRMSG 2C1 4 ICBPRO 15A 80 4 ICBPROF 15A 40 4 ICBPROG 15B 80 4 ICBPRULS 102 4 ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRUL8 109 5 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBROSFL 408 3				
ICBPRO 15A 80 4 ICBPROF 15A 40 4 ICBPROG 15B 80 4 ICBPRULS 102 4 ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRUL8 109 5 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBROSFL 408 3				
ICBPROF 15A 40 4 ICBPROG 15B 80 4 ICBPRULS 102 4 ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRUB 109 5 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBROGSN 36C 3 ICBRDSFL 408 3				
ICBPROG 15B 80 4 ICBPRULS 102 4 ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRULS 102 4 ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRUB 100 4 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRUL1 102 5 ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3			80	
ICBPRUL2 103 5 ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRUL3 104 5 ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRUL4 105 5 ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRUL5 106 5 ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRUL6 107 5 ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRUL7 108 5 ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRUL8 109 5 ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPRVOK FE 3 ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPSLEN 100 4 ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPSYN 100 3 ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBPWARN FF 3 ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBQLLN 164 3 ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBQUAL 165 3 ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBRCGSN 36C 3 ICBRDSFL 408 3				
ICBRDSFL 408 3				
ICBRDSN C4 08 4				
	ICBRDSN	C4	08	4

	Hex	Hex	
Name	Offset	Value	Level
ICBRETP	162		3
ICBRSVD	A27		2
ICBSAUD	C7	10	4
ICBSBYS	38A	10	4
ICBSESS	389	80	4
ICBSINT	31A		3
ICBSLAU	16E		3
ICBSLCL	382	80	4
ICBSLVL	161		3
ICBSMCT	3EC		3
ICBSPAUD	372		3
ICBSPCTL	37A		3
ICBSTAT	C2		3
ICBSTAT1	C4		3
ICBSWPW	174		3
ICBTAPE	C4	80	4
ICBTDSN	159	40	4
ICBTEMP	22		3
ICBTERP	C7	80	4
ICBTMPAL	20E		3
ICBTMPRL	206		3
ICBTMPLV	420		3
ICBTMPVR	206		3
ICBTUAC	C7	40	4
ICBTXLN	21C		3
ICBTXRBA	216		3
ICBUMCT	418		3
ICBUSCT	40C		3
ICBVAUDC	727		3
ICBVFPTC	6A7		3
ICBVGCMC	527		3
ICBVGENC	4A7		3
ICBVGNL	627		3
ICBVLGA	827		3
ICBVLGF	9A7		3
ICBVLGS	927		3
ICBVLNV	8A7		3
ICBVMSSP	2A6		3
ICBVMSXA	2AA		3
ICBVPROC	427		3
ICBVRCL	5A7		3
ICBVRMN	3FA		3
ICBVSTAC	7A7		3
ICBWIP	1A	08	4
ICCIBRBA	8		3
ICISSRBA	Е		3
ICNTMPCT	205		3
ICTMPCNT	1B		3
ICTMPL	22		4
ICTMPN	24		4
ICTMPNN	208		4
ICTMPRBA	26		4
ICBTMPRL	206		4
	* *		•

	Hex	нех	
Name	Offset	Value	Level
ICTMRSV1	25		4
ICTMRSV2	2C		4
ICTSEGLN	400		3
ICTSEGRB	402		3
INVICB	0		1

Appendix B. The Security Product Trace Area (SAFT)

The SAFT is included here to help you diagnose RACF problems.

Common Name: RACF Security Product Trace Area Control Block

Macro ID: IRRSAFT DSECT Name: SAFT

Owning Component: Resource Access Control Facility (SC1BN)

Eye-Catcher ID: SAFT Offset: 0

Offset: 0 Length: 4

Storage Attributes:

Subpool: 245
Key: 0
Residency: SQA

Size: 200 bytes

Created by: ICHSEC07 during RACF initialization. **Pointed to by:** SAFVSECT in the SAFV data area

Serialization: This control block is serialized with SYSZRAC2 ENQ.

Function: The SAFT provides a communication area for information global to the SAF Trace

utility.

Offset	Offset				
(Dec)	(Hex)	Туре	Len	Name (Dim)	Description
0	(0)	STRUCTURE		SAFT	IRRSAFT Control Block
0	(0)	CHARACTER	4	SAFTID	SAFT eyecatcher
4	(4)	UNSIGNED	1	SAFTVRSN	Version Number
5	(5)	CHARACTER	3	*	RESERVED
8	(8)	UNSIGNED	1	SAFTSUBP	Storage subpool
9	(9)	UNSIGNED	3	SAFTLENG	Length of SAFT
12	(C)	UNSIGNED	4	SAFTTRCO	Trace routine address
16	(10)	UNSIGNED	4	SAFTTRPC	Trace routine PC number
20	(14)	BITSTRING	4	SAFTTRAC	RACF trace flags
20	(14)	BITSTRING	1	SAFTTACT	RACF trace flags
		1		SAFTACTV	A trace is active
		.1		SAFTRRTE	Trace racroute events
		1		SAFTMGRT	Trace DB manager events
		1		SAFTSYSC	Trace system calls
		1		SAFTSYSZ	Trace SAF3 calls
		111		*	RESERVED
21	(15)	BITSTRING	3	*	RESERVED
24	(18)	BITSTRING	8	SAFTRRTR	Racroute events
24	(18)	BITSTRING	1	*	
		1		SAFTRALL	Trace all racroutes
		.1		SAFTAUTH	SAFPREQT = 1 (Auth)
		1		SAFTFAUT	SAFPREQT = 2 (Fastauth)
		1		SAFTLIST	SAFPREQT = 3 (List)
		1		SAFTDEFN	SAFPREQT = 4 (Define)
		1		SAFTVFY	SAFPREQT = 5 (Verify)
		1.		SAFTEXTR	SAFPREQT = 6 (Extract)
		1		SAFTDIR	SAFPREQT = 7 (Dirauth)
25	(19)	BITSTRING	1	*	
		1		SAFTTKSR	SAFPREQT = 8 (Token Serv)
		.1		SAFTVFYX	SAFPREQT = 9 (VerifyX)

Offset	Offset	Tuna		Nama (Dim)	Decementary
(Dec)	(Hex)			Name (Dim)	Description
		1		SAFTTEXT	SAFPREQT = A (Token Serv)
		1		SAFTTBLD	SAFPREQT = B (Token Bld.)
		1		SAFTTXBR	SAFPREQT = C (Extract BR=Y)
		1		SAFTAUD	SAFPREQT = D (Audit)
		1.		SAFTTSTS	SAFPREQT = E (Status)
		1		SAFTSIGN	SAFPREQT = F (Signon)
26	(1A	BITSTRING	1		
		1		SAFTMPX	SAFPREQT = 10 (Tmap Xmem)
		.1		SAFTTXTX	SAFPREQT = 11 (Text Xmem)
		11 1111		*	RESERVED
27		BITSTRING	5	*	RESERVED
32	, ,			SAFTSCLS	Trace RACF syscalls
32	(20)	BITSTRING	1	*	
		1		SAFTSALL	Trace all syscalls
		.1		SAFTSIU0	Init USP
		1		SAFTSDU0	Delete USP
		1		SAFTSMF0	Make FSP
		1		*	RESERVED
		1		SAFTSMM0	Set File Mode Creation Mask
		1.		SAFTSKA0	Check Access
		1		SAFTSKP0	Check Priviledge
32	(22)	BITSTRING	1		
		1		SAFTSUM0	Get Umap
		.1		SAFTSGM0	Get Gap
		1		SAFTSGG0	Get Supplimental Groups
		1		SAFTSSU0	Set Uid
		1		SAFTSEU0	Set Effective Uid
		1		SAFTSSG0	Set Gid
		1.		SAFTSEG0	Set Effective Gid
0.4	(00)	1		SAFTSCO0	Change Owner Group
34	(22)	BITSTRING	1		Ol (II)
		1		SAFTSCF0	Change file mode
		.1		SAFTSCA0	Change file audit options Exec Set Uid, Gid
		1		SAFTSEX0 SAFTSAU0	Audit
		1		SAFTSKO0	Check Process owner
		1		SAFTSQS0	Query Security options
		1.		SAFTSQ50	Query File options
		1		SAFTSCS0	Clear SETID
35	(23)	BITSTRING		*	Clear SETID
33	(23)	1	•	SAFTSKF0	Check File Owner
		.1		SAFTSMR0	Make Root FSP
		1		SAFTSPT0	PTRACE Authority Check
		1		SAFTSUG0	Get User groups
		1		SAFTSFK0	Fork Exit
		1		SAFTSMI0	Make ISP
		1.		SAFTSKI0	Check IPC
		1		SAFTSCI0	IPC Control
36	(24)	BITSTRING		*	
	()	1		SAFTSC20	Check Owner 2 Files
		.1		SAFTSGE0	Get EUid/EGid SupGrp
		1		SAFTSDI0	R_dceinfo
		1		SAFTSDK0	R_dcekey
					= · · · · · · · ·

Offset	Offset	Tuna	Lan	Nama (Dim)	Description
(Dec)	(Hex)		Len	Name (Dim)	Description
		1		SAFTSUD0	R_dceruid
		1		SAFTSDA0	R_dceauth
		1.		SAFTSIA0	InitAcee
37	(25)	1 BITSTRING	1	SAFTSEQ0 *	RACF Admin Request
		1		SAFTSIM0	User Map
		.1		SAFTSDL0	R_datalib
		1		SAFTSMK0	Kerb
		1		SAFTSPK0	Ticket Serve
		1		SAFTSPX0	R_PKIServ
		1		SAFTSCH0	R_cacheserv
		1.		SAFTSPY0	R_proxyserv
		1		SAFTSCL0	R_SetFacl
38	(26)	BITSTRING	10		RESERVED
48		BITSTRING		SAFTZCLS	Trace SAF3 calls
48		BITSTRING	1		
.0	(00)	1		SAFTZALL	All SAF3 clls
		.1		SAFTZA00	aznAccess
		1		SAFTSC00	aznCreds
		1111		*	RESERVED
49	(31)	BITSTRING	7	*	RESERVED
56		BITSTRING	-	SAFTMTRC	Trace DB manager events
56		BITSTRING	1		Trace BB manager events
30	(00)	1	'	SAFTMLL	All DB manager event reads
		.1		SAFTMRD	reads
		1		SAFTMALT	writes
		1		SAFTMALI	alteri
		1111		*	RESERVED
57	(30)	BITSTRING	7	*	RESERVED
64		ADDRESS	-	SAFTRRPR	Address of pre-function call
04	(40)	ADDITESS	4	SAI IIIII II	indicator
68	(44)	ADDRESS	4	SAFTRRPS	Address of post-function call
					indicator
72	(48)	ADDRESS	4	SAFTSCPR	Address of pre-function call indicator
76	(4C)	ADDRESS	4	SAFTSCPS	Address of post-function call
					indicator
80	(50)	ADDRESS	4	SAFTZCPR	Address of pre-function call indicator
84	(54)	ADDDESS	1	SAFTZCPS	Address of post-function call
04	(54)	ADDRESS	4	SAFIZOFS	indicator
88	(58)	ADDRESS	4	SAFTMGPR	Address of pre-function call
					indicator
92	(5C)	ADDRESS	4	SAFTMGPS	Address of post-function call indicator
96	(60)	ADDRESS	16	*	RESERVED
112	(70)	ADDRESS	4	SAFTALST	Trace ASID LIST
116	(74)	ADDRESS		SAFTJLST	Trace JOBS LIST
120	(78)	ADDRESS	16	*	RESERVED
136	(88)	CHARACTER	16	SAFTRRL	Flags to the security product
136	(88)	CHARACTER	8	SAFTRPRE	Pre process flag
144	(90)	CHARACTER	8	SAFTRPOS	Post process flag
152	(98)	CHARACTER	16	SAFTSCFL	Flags to the security product
152	(98)	CHARACTER	8	SAFTSPRE	Pre process flag

SAFT

Offset	Offset				
(Dec)	(Hex)	Туре	Len	Name (Dim)	Description
160	(A0)	CHARACTER	8	SAFTSPOS	Post process flag
168	(A8)	CHARACTER	16	SAFTZCFL	Flags to the PD product
168	(A8)	CHARACTER	8	SAFTZPRE	Pre process flag
176	(B0)	CHARACTER	8	SAFTZPOS	Post process flag
184	(B8)	CHARACTER	16	SAFTMGFL	Flags to the security product
184	(B8)	CHARACTER	8	SAFTMPRE	Pre process flag
192	(C0)	CHARACTER	8	SAFTMPOS	Post process flag

End of SAFT mapping

Appendix C. IPCS formatting for RACF control blocks

This topic explains how to analyze RACF dump information by providing formatting support for RACF control blocks by using IPCS formatting.

IPCS formatting is intended only for diagnosis use when requested by the IBM support center.

Using the VERBX RACFDATA command

Use the VERBX RACFDATA command, without any options, to provide a list of acceptable report options. The following report options are provided:

RRSF

ı

I

Shows remote requests which are actively being processed on a RACF address space TCB, as well as any requests that are queued for execution. The output summarizes the requests being processed and provides output containing commands. For example:

IP CBF 00067F28 ASID(x'001E') STR(IRRSSTCB) EXIT

For more information, cut and past the IP CBF command line to the command input area in the IPCS screen:

```
IPCS OUTPUT STREAM ------ Line 0 Cols 1 78
Command ===> IP CBF 00067F28 ASID(x'001E') STR(IRRSSTCB) EXIT SCROLL ===> CSR
```

Press ENTER and you will see the control block you requested. Press PF3 to return to the previous control block.

CDT

Shows class descriptor table information, including static and dynamic class descriptors. Static is the common storage and most frequently available. Dynamic are in a data space and usually not dumped. Both CDTs are pointing to structures that reside in RACF data spaces. The formatting code attempts to locate the data space in the dump, but if it is not present, a message is issued identifying the data space that is missing from the dump.

If there is a problem with CDT processing, request a dump that includes RACF data spaces. The option to use on the DUMP or SLIP command is:

```
DSPNAME=(1.IRR*)
```

This dumps all data spaces owned by ASID(1) that start with IRR.

DSDT

Shows information about all active primary and backup RACF data sets.

DSG

Shows information about requests from other systems in the sysplex.

Using the SUMMARY FORMAT command

When using the SUMMARY FORMAT command it drives the invocation of exits for control blocks that it formats. The RACF IPCS support provides exits for ASXB, TCB, STCB and RBs. These exits look for data that is relevant to RACF for the control block. For example, ASXBSENV and TCBSENV may point to an ACEE. When this field is non-zero, then the exit generates output:

IP CBF 009EC300 ASID(X'0067') STR(ACEE) EXIT

IPCS

For more ACEE information, cut and paste this command to the command line and run it. The EXIT option on the CBF command causes an ACEE exit to get control which formats different extensions on the ACEE. This enables you, for example, to see the list of groups that the userid is connected to.

The STCB exit looks for the presence of a RACD and generates a command:

IP CBF 7FFFAD00 ASID(X'0067') STR(IRRPRACD)

RB is the most frequent exit. The RB exit determines whether it is an SVRB and if the SVRB was created for SVC 82, 83, 84 or 85 (all the RACF SVCs). For each SVC, there is a SAF parameter list and a function unique parameter list. The RB exit identifies the function being called, who invoked the SVC and CBF commands to format any parameter lists that are present. For example:

The previous RB has called RACF SVC 82 for function RACHECK Return address of SAF caller: 00D2A93A ASID(X'0018') D2A93A. IFG0194A+293A IN PLPA IP CBF 008D1D40 ASID(X'0018') STR(ICHSAFP) IP CBF 008D1D68 ASID(X'0018') STR(ICHACHKL)

For more information on parameter lists, see Parameter list descriptions.

Using the Control Block Formatters

You can format many of the control blocks RACF uses. See "Using the SUMMARY FORMAT command" on page 257 for examples. Also, see the RCVT, by using the CBF ICHPRCVT command, for another example, which can be useful to find your active exits. A complete list can be found in the results of IPCSDATA CURRENT ACTIVE.

Appendix D. IBM Health Checker for z/OS

IBM Health Checker for z/OS is a tool that checks the current active z/OS settings and definitions for an image and compares their values to either those suggested by IBM or defined by you. The objective of the IBM Health Checker for z/OS is to identify potential problems before they impact your availability or, in worst cases, cause outages. The tool produces reports (snapshots of your system) to help you analyze the values defined for this system.

For more information, see IBM Health Checker for z/OS: User's Guide.

IBM Health Checker for z/OS RACF checks

The following checks directly support the RACF environment and configuration. The checks make recommendations for the following areas:

- Customization of the global resource serialization (GRS) environment. This
 ensures that RACF serialization ENQs and RESERVEs are processed correctly.
- · The remaining checks examine the security configuration of the environment.

These checks can help eliminate system outages, minimize exposures, optimize performance. The check names are:

RACF_FACILITY_ACTIVE

RACF_GRS_RNL

RACF_IBMUSER_REVOKED

RACF OPERCMDS ACTIVE

RACF SENSITIVE RESOURCES

RACF TAPEVOL ACTIVE

RACF TEMPDSN ACTIVE

RACF_TSOAUTH_ACTIVE

RACF_UNIXPRIV_ACTIVE

Note that checks can be individually overridden or customized to fit a particular installation. See the check listing in *IBM Health Checker for z/OS: User's Guide* for more information.

Appendix E. Accessibility

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, to use software products successfully. The major accessibility features in z/OS enable users to:

- Use assistive technologies such as screen readers and screen magnifier software
- · Operate specific or equivalent features using only the keyboard
- · Customize display attributes such as color, contrast, and font size

Using assistive technologies

Assistive technology products, such as screen readers, function with the user interfaces found in z/OS. Consult the assistive technology documentation for specific information when using such products to access z/OS interfaces.

Keyboard navigation of the user interface

Users can access z/OS user interfaces using TSO/E or ISPF. Refer to z/OS TSO/E Primer, z/OS TSO/E User's Guide, and z/OS ISPF User's Guide Vol I for information about accessing TSO/E and ISPF interfaces. These guides describe how to use TSO/E and ISPF, including the use of keyboard shortcuts or function keys (PF keys). Each guide includes the default settings for the PF keys and explains how to modify their functions.

z/OS information

z/OS information is accessible using screen readers with the BookServer/Library Server versions of z/OS books in the Internet library at:

http://www.ibm.com/systems/z/os/zos/bkserv/

Notices

This information was developed for products and services offered in the USA. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation Licensing 2-31 Roppongi 3-chome, Minato-ku Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs

Notices

and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation Mail Station P300 2455 South Road Poughkeepsie, NY 12601-5400 USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

This product contains code licensed from RSA Data Security Incorporated.



Programming interface information

This z/OS Security Server RACF Diagnosis Guide documents information that is NOT intended to be used as a programming interface of z/OS.

Policy for unsupported hardware

Various z/OS elements, such as DFSMS[™], HCD, JES2, JES3, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

BookManager

CICS

CICS/ESA

DB2

DFSORT

IBM

IBMLink

IBM Redbooks

IMS

Library Reader

Linex

MVS

OS/390

RACF

RETAIN

S/390

SecureWay

System/390

TalkLink

VM/ESA

VTAM

z/OS

zSeries

Lotus and Lotus Notes are trademarks of Lotus Development Corporation in the United States, other countries, or both.

NetView, TME, and Tivoli are trademarks of International Business Machines Corporation or Tivoli Systems Inc. in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.

Index

Special characters	BLKUPD command (continued)
??? state 142	invoking 124
::: State 142	LOCATE subcommand 125
	locating an index entry 125
Α	READ subcommand 126
	syntax of 124
abend	terminating 135
example of search argument 37	updating a RACF block 126
incorrect output 22	block update command (BLKUPD) 122
VRA keys provided by RACF 234	
worksheet for reporting problems 100	0
abends	C
troubleshooting table 9	callable services
access to a directory	error recording 193
directory 48 accessibility 261	process flow 193
ACEE	Callable Services
control block overview 223	dump title description 231
ACTNPTR symptom in DAEDATA output 234	tracing 52
administration, RACF	caller of RACF, identifying 78
classroom courses xiv	CHANGE subcommand of BLKUPD DISPLAY
alias index blocks	subcommand 131
description of 111	checking the parameter list passed to RACF 79
ALL keyword	class identifier
on BLKUPD LIST subcommand 128	adding to profile names 118
APPC	CLASS keyword
errors initializing connections 145	on BLKUPD DISPLAY subcommand 130, 131, 132
obtaining trace records 50	classname
restarting a stopped task 146	on LOCATE subcommand of BLKUPD 125
return code handling 146	classroom courses, RACF xiv collecting problem data for RACF 41
application identity mapping	command
examples 82	BLKUPD 122
handling 81	front-ending 235
IRRIRA00 81	incorrect output 23
ASID events	trace records 50
obtaining trace records 50	command procedures
ASXB control block overview 224	executing BLKUPD under control of 123
attention handling	command traces 50
when using BLKUPD 123	COMP keyword
AUDIT request	on CHANGE subcommand of BLKUPD DISPLAY
parameter list 155	subcommand 131
AUTH requests	on INSERT subcommand of BLKUPD DISPLAY
parameter list 156	subcommand 133
	component identification for RACF 35
В	compression count, front-end 114
BAM blocks	connection state changes 141
block masks 109, 110	connection states of RRSF nodes 141, 143
description of 107, 109	control block
format of the header 109	ACEE 223
BLKUPD command	ASXB 224
authority required for 122	GRPF 223
considerations 122	ICB 241
DATA command procedure statement 123	inventory 241
description of 122	RCVT 223
END subcommand 135	SAF router vector table 223
ENDDATA command procedure statement 123	task control block (TCB) 224 courses about RACF xiv
examples 136	Socious about Finoi Aiv

D	DIRAUTH request
D-B state 142	parameter list 166
D-E state 142	directed commands
D-L state 142	process flow 186
D-R state 142	dirty bit 44
DATA command procedure statement	controlled programs 44
when executing BLKUPD 123	disability 261
data encryption standard (DES)	DISPLAY subcommand of BLKUPD READ
algorithm 28	subcommand 130
database 121	distributed environment
BAM blocks 109	types of errors 140
BLKUPD command 122	documentation
first record 241, 253	troubleshooting table 19
format 107	documentation error
header block 108	example of search argument 37
how RACF creates and names profiles 118	worksheet for reporting problems 100
incorrect output 25	dormant by local request state 142 dormant by mutual request state 142
index blocks 111, 112	dormant by mutual request state 142 dormant by remote request state 142
index entries 113, 116	dormant in error state 142
inventory control block (ICB) 241	DSECTs
IRRDBU00 utility 107	INVICB 241
modifying with BLKUPD 122	SAFT 253
security product trace area(SAFT) 253	DSMON
sequence set chain pointers 117	incorrect output 23
tape volumes 118	dump title descriptions
templates 108	Callable Services 231
troubleshooting 107	ICHRST00-RACF SVCS 224
types of records in	IRRCOP10 module 227
BAM blocks 107, 109	IRRRLS12 module 227
header block 107, 108	IRRRLS13 module 228
index blocks 107, 110, 111	IRRRLS14 module 228
profiles 107	IRRRLS15 module 229
templates 107, 108	RACF initialization failure 226
unloading to a sequential file 107	RACF persistent verification dumps 230
using READ subcommand of BLKUPD to update a	RACF subsystem dumps 229
block 126	RACF/DB2 external security module 232
viewing with BLKUPD 122	SVC 224, 232
DATABASE events	DUPLICATE keyword
obtaining trace records 50 database profile	on CHANGE subcommand of BLKUPD DISPLAY
class identifier 118	subcommand 132
description of templates 108	on INSERT subcommand of BLKUPD DISPLAY
database unload utility (IRRDBU00)	subcommand 133
common problems 4	
using 107, 121	_
DB2	E
See RACF/DB2 external security module	END subcommand
DEBUG command 237	of BLKUPD command 135
DEF state 142	of BLKUPD DISPLAY subcommand 134
DEFINE request	of BLKUPD READ subcommand 135
parameter list 160	ENDDATA command procedure statement
defined state 142	when executing BLKUPD 123
definition errors for RRSF 140	ENTRY keyword
DELETE subcommand	on BLKUPD DISPLAY subcommand 130
of BLKUPD READ DISPLAY subcommand 133	on CHANGE subcommand of BLKUPD DISPLAY
DES (Data Encryption Standard)	subcommand 131
algorithm 28	on INSERT subcommand of BLKUPD DISPLAY
diagnosis	subcommand 132
hints 2	entryname
problems in racf 1	on LOCATE subcommand of BLKUPD 125
procedures for RACF 1	environmental errors for RRSF 140

error recording	header block
for callable services 193	description of 107, 108
for RRSF 148	fields in 241, 253
error recovery for RACF sysplex data sharing	format 108
actions 239	
consequences 240	
errors	1
definition errors for RRSF 140	ICB (inventory control block)
environmental errors for RRSF 140	description of 107, 108
program errors for RRSF 140	fields in 241
transmission/line errors 140	format 108
errors in a distributed environment 140	ICHEINTY macro
ESTAE processing for RRSF 144	common problems 6
EXTRACT request	parameter list 182
parameter list 167	ICHRST00 module
	dump title for certain abends 224
_	ICHSEC00 module
F	dump title for certain abends 226
failure keywords	RACF initialization failure 226
for a complete search 80	ICHSEC02 module
for a preliminary search 33	dump title for initialization failure 226
failure of an MVS system service 144	identifying
FASTAUTH request	the caller of RACF 78
parameter list 169	IMAGE events
FIND subcommand of READ subcommand of	obtaining trace records 50
BLKUPD 127	incorrect output
finding RACF information xiii	example of search argument 37
FMIDs for RACF 38	troubleshooting table 20
format of the RACF database 107	worksheet for reporting problems 100
FORMAT subcommand of BLKUPD READ	independent RACF system macros
subcommand	equivalent RACROUTE REQUEST types 151
format of 128	index blocks
list of the information displayed 128	compression of index entries 114
FRACHECK macro	description of 107, 110, 111
equivalent RACROUTE REQUEST type 151	format of 111, 112
free-format search	header 112, 113
examples of symptoms for RACF 34, 81	index entries 113, 116
front-end compression count 114	sequence set chain pointers 117
front-ending commands 235	how profiles are located 110, 111
front-ending processor 235	information listed by the FORMAT
	subcommand 128
G	index entries
	compression of 114
general macro	format of 113
common problems 6	locating in a sequence set 125
GENERIC keyword	index entry table
on BLKUPD DISPLAY subcommand 130	sequence set chain pointers 117
on CHANGE subcommand of BLKUPD DISPLAY	index structure
subcommand 131	example of 111 Information/Access
on INSERT subcommand of BLKUPD DISPLAY	use for RACF problem searches 34
subcommand 133	Information/Management
on LOCATE subcommand of BLKUPD 125	use for RACF problem searches 34
GRPF control block overview 223	Information/MVS
GTF traces 43, 44, 48, 50	use for RACF problem searches 34
	Information/System
Н	use for RACF problem searches 34
	initial state 142
handshaking 141	initialization problem
header	dump title for initialization failure 226
for BAM blocks 109	INMSG data set for RRSF 139, 141
for index blocks 112, 113	

INSERT subcommand of BLKUPD DISPLAY subcommand 132 installation exit process flow 188 inventory control block (ICB) description of 107	LISTALL keyword on LOCATE subcommand of BLKUPD 125 LOCATE subcommand of BLKUPD format of 125 locating an index entry 125 logon problems 28
fields in 241 format of 107	troubleshooting table 28 worksheet for reporting problems 101
INVICB DSECT 241 IPCS (interactive problem control system) 8 IPCS formatting for RACF control blocks	LOGREC data set entries for callable services errors 193 for RRSF errors 148
IPCS 257 IPLPTR symptom in DAEDATA output 234	loop diagnostic procedures 29
IRRBRW00 utility 148 IRRCOP10 module dump title for failed data space 227	example of search argument 37 troubleshooting table 29 worksheet for reporting problems 102
IRRDBU00 utility common problems 4	
using database unload utility 107	M
IRRENV00 module 235	macros
IRRRID00 utility	checking parameter lists 79
common problems 5	ICHPICB 241
process flow 190	incorrect output 27
IRRRLS12 module	IRRSAFT 253
dump title for COPY RACGLIST 227	process flow 187
IRRRLS13 module	return codes 32
dump title for CREATE RACGLIST 228	masks
IRRRLS14 module dump title for DELETE RACGLIST 228	block masks in the RACF database 109, 110
IRRRLS15 module	matching problem
dump title for data space recovery failure 229	searching for a 80
IRRSSC01 module	message
dump title for RACF subsystem 229	example of search argument 37
IRRSSS01 module	troubleshooting table 29 worksheet for reporting problems 103
dump title for RACF subsystem 229	messages
IRRTEMP2 member of SYS1.MACLIB	incorrect output 21
used by IRRMIN00 108	MGRREQST symptom in DAEDATA output 234
IRRUT100 utility	MVS router
common problems 3	parameter list 152
IRRUT200 utility	parameter 1.02
common problems 3	NI.
IRRUT400 utility	N
common problems 4	NEW keyword
	on FIND subcommand 127
J	on FORMAT subcommand 128
_	on LIST subcommand 128
JOBNAME events	NEXT subcommand of BLKUPD READ DISPLAY
obtaining trace records 50	subcommand 133
	nodes, RRSF
K	connection states 141
keyboard 261	connection states after TARGET 143 NODUPLICATE keyword
	on CHANGE subcommand of BLKUPD DISPLAY subcommand 132
L	on INSERT subcommand of BLKUPD DISPLAY
level of failing module 81	subcommand 133
LIST request	non-VSAM data set
parameter list 170	used for the RACF database 107
LIST subcommand of BLKUPD READ subcommand	NOSAVE keyword
format of 127	on BLKUPD END subcommand 135

NOSAVE keyword <i>(continued)</i> on END subcommand of BLKUPD DISPLAY subcommand 134 not defined state 142	parameter list (continued) SIGNON service 171 STAT service 172 TOKENBLD service 173 TOKENEXTR service 177
0	TOKENMAP service 177
_	VERIFY service 178
O-A state 142	VERIFY/VERIFYX service parameter list 181
O-E state 142	VERIFYX service 178 PassTicket
O-P-C state 141	
O-P-V state 142	logon problems 28
OFFSET keyword	performance
on BLKUPD REPLACE subcommand 129	example of search argument 37
OLD keyword	troubleshooting table 31 worksheet for reporting problems 103
on BLKUPD FIND subcommand 127	persistent verification
on BLKUPD FORMAT subcommand 128	dump title for RACF subsystem 230
on BLKUPD LIST subcommand 128	preliminary search for a matching problem 33
operative active state 142	problem diagnosis
operative needing connection state 141	making sure this is a RACF problem 2
operative pending connection state 141	procedures for RACF 1
operative pending verification state 142 OUTMSG data set for RRSF 139, 141	problem reporting procedure for RACF 99
output, incorrect	process flow
troubleshooting table 20	RACF callable services 193
worksheet for reporting problems 100	RACF commands 185
worksheet for reporting problems 100	RACF directed commands 186
	RACF installation exits 188
P	RACF macros 187
PADS (program access to data sets) 44	RACF remove ID utility 190
parameter list	RACF report writer 191
AUDIT service 155	RACF utilities 190
AUTH service 156	SMF data unload utility 192
checking 79	profile
cross reference for RACROUTE REQUEST	class identifier 118
types 151	description 117
DEFINE service 160	description of templates 108
descriptions 151	displayed by BLKUPD, example of 120
DIRAUTH service 166	how RACF locates 110, 111
EXTRACT service 167	program access to data sets (PADS) 44
FASTAUTH service 169	program control
ICHEINTY 182	determining programs that need protection 44
list passed to RACF 79	program errors for RRSF 141
LIST service 170	publications on CD-ROM and DVD xiv
MVS router 152	softcopy xiv
obtaining 43, 48	Solicopy XIV
RACROUTE 152	
RACROUTE REQUEST=AUDIT 155	R
RACROUTE REQUEST=AUTH 156	R_admin callable service
RACROUTE REQUEST DIPAUTU 166	tracing 52
RACROUTE REQUEST=DIRAUTH 166 RACROUTE REQUEST=EXTRACT 167	RACDEF macro
RACROUTE REQUEST=EXTRACT 167 RACROUTE REQUEST=FASTAUTH 169	equivalent RACROUTE REQUEST type 151
RACROUTE REQUEST=FASTAUTH 109 RACROUTE REQUEST=LIST 170	RACF
RACROUTE REQUEST=SIGNON 171	publications
RACROUTE REQUEST=SIGNON 171 RACROUTE REQUEST=STAT 172	on CD-ROM and DVD xiv
RACROUTE REQUEST=STAT 172 RACROUTE REQUEST=TOKENBLD 173	softcopy xiv
RACROUTE REQUEST=TOKENEED 173 RACROUTE REQUEST=TOKENEXTR 177	RACF blocks
RACROUTE REQUEST=TOKENMAP 177	updating 126
RACROUTE REQUEST=VERIFY 178	RACF callable services
RACROUTE REQUEST=VERIFYX 178	process flow 193
SAF router 152	·

RACF commands	RACINIT macro
process flow 185	equivalent RACROUTE REQUEST type 151
RACF database	RACLIST macro
See database	equivalent RACROUTE REQUEST type 151
RACF Database Managers Request	RACROUTE
tracing 52	trace service type number 56
RACF directed commands	RACROUTE events
process flow 186	obtaining trace records 50
RACF FMIDs 38	RACROUTE macro
RACF index block errors	common problems 7
description 231	parameter list 152
RACF installation exits	RACROUTE REQUEST types
process flow 188	equivalent RACF system macros 151
RACF macros	RACROUTE REQUEST=AUTH macro
how to locate parameters in a dump 79	parameter list 156
ICHEINTY parameter list 182	RACROUTE REQUEST=DEFINE macro
obtaining parameter list for RACROUTE 43, 48	parameter list 160
process flow 187	RACROUTE REQUEST=EXTRACT macro
RACF macros and utilities	parameter list 167
common problems 3	RACROUTE REQUEST=FASTAUTH macro
RACF macross	
	diagnosing failures to grant access 232
common problems 6	parameter list 169 RACROUTE REQUEST=LIST macro
RACF manager	
adding a class identifier to profile names 118	parameter list 170
RACF problems	RACROUTE REQUEST=SIGNON macro 171
data for 41	parameter list 171
reporting to IBM 99	RACROUTE REQUEST=STAT macro 172
searching for a matching problem 80	parameter list 172
RACF profile	RACROUTE REQUEST=TOKENBLD macro
description 117	parameter list 173
RACF reason codes	RACROUTE REQUEST=TOKENMAP/TOKENXTR
in the RACF/DB2 external security module 232	macros
obtaining 42	parameter list 177
RACF remote sharing facility	RACROUTE REQUEST=VERIFY macro
See RRSF (RACF remote sharing facility)	parameter list 178
RACF remove ID utility	Racroutes
process flow 190	tracing 52
RACF report writer	RACSTAT macro
process flow 191	equivalent RACROUTE REQUEST type 151
RACF return codes	RACXTRT macro
in the RACF/DB2 external security module 232	equivalent RACROUTE REQUEST type 151
obtaining 42	RANGE keyword
RACF SMF data unload utility	on BLKUPD LIST subcommand 128
process flow 192	RBA (relative byte address)
RACF subsystem module	on READ subcommand of BLKUPD 126
dump title for RACF subsystem 229	used in locating a profile 110, 111
RACF subsystem dumps 229	RBA keyword
RACF utilities	on CHANGE subcommand of BLKUPD DISPLAY
common problems 3	subcommand 131
IRRDBU00 121	on INSERT subcommand of BLKUPD DISPLAY
process flow 190	subcommand 133
RACF/DB2 external security module	RCVT
diagnostic information 232	control block overview 223
dump titles 232	READ subcommand of BLKUPD
XAPLDIAG output parameter 232	END subcommand 135
RACFCNTS symptom in DAEDATA output 234	FIND subcommand 127
RACFRW utility	for reading a RACF database block 127
common problems 6	for updating a RACF database block 127
RACHECK macro	format of 126
equivalent RACROUTE REQUEST type 151	FORMAT subcommand 128
,	LIST subcommand 127

READ subcommand of BLKUPD (continued)		REVOKE attribute in user profile 28
REP subcommand 129		RRSF (RACF remote sharing facility)
REREAD subcommand 135		connection states 141
reading every profile in your database		connection states after TARGET 143
using the database unload utility (IRRDBU00)	107	defined state 142
reason codes		dormant by local request state 142
from callable service 43		dormant by mutual request state 142
from RACF macros 42, 43		dormant by remote request state 142
obtaining 42		dormant in error state 142
recording of errors		error recording 148
for callable services 193		ESTAE processing 144
RRSF 148		failure recovery 143
records		initial state 142
in the RACF database		INMSG data set 139, 141
BAM blocks 109		introduction 139
index blocks 110, 111		IRRBRW00 utility 148
profiles 117		LOGREC data set entries 148
recovery procedures		not defined state 142
APPC errors 145		
		operative in error state 142
failure of MVS system service 144		operative pending connection state 141
RRSF ESTAE processing 144		operative pending connection state 141
RRSF failure 143		operative pending verification state 142
VSAM failures 147		OUTMSG data set 139, 141
relative byte address (RBA) 126		RRSFLIST data set 148
remote sharing		workspace data set 139, 141
See RRSF (RACF remote sharing facility)		dumping the data in 148
remove ID utility (IRRRID00)		RRSFLIST data set
common problems 5		recording of errors 148
process flow 190		
REP subcommand of BLKUPD READ		S
subcommand 129		3
report writer		SAF return codes
common problems 6		in the RACF/DB2 external security module 232
incorrect output 23		SAF router
process flow 191		parameter list 152
reporting problems to IBM		SAF router vector table
abend 100		control block overview 223
documentation error 100		SAFT (security product trace area)
incorrect output 100		fields in 253
information to collect 100		SAFT DSECT 253
logon 101		save area
loop 102		use for validating input parameters 79
messages 103		SAVE keyword
overview 99		on BLKUPD END subcommand 135
performance 103		on END subcommand of BLKUPD DISPLAY
return code 104		subcommand 134
wait 105		SDWA (system diagnostic work area)
REREAD subcommand of BLKUPD READ		sample for RACF 235
subcommand 135		search arguments
RESTART command		examples 33, 37
using to recover from failures 146		search symptoms
RETAIN symptom string		for a complete search 80
sample in DAEDATA output 234		for a preliminary search 33
sample in formatted dump 234		security product trace area(SAFT)
return codes		fields in 253
example of search argument 37		security topics for RACF
from callable service 43		classroom courses xiv
from RACF macros 42		SEGMENT keyword
obtaining 42		on BLKUPD DISPLAY subcommand 133
troubleshooting table 32		on CHANGE subcommand of BLKUPD DISPLAY
worksheet for reporting problems 104		
		subcommand 131

segment table block 109	terminal monitor program
sequence set	executing BLKUPD under 123
definition of 110, 111	TESTPTR symptom in DAEDATA output 234
format of the chain pointers 117	TMP (terminal monitor program)
locating an index entry 125	executing BLKUPD under 123
sequential file	TOKENBLD request
creating for further manipulation 107	parameter list 173
using the database unload utility (IRRDBU00) 107	TOKENEXTR request
shortcut keys 261	parameter list 177
SIGNON request	TOKENMAP request
parameter list 171	parameter list 177
SLIP trap	trace area
•	SAFT 253
setting 41	
SMF data unload utility	traces
process flow 192	for callable services 52
SMF records	for R_admin callable service 52
incorrect output 24	for RACF Database Managers Requests 52
STAT request	for racroutes 52
parameter list 172	obtaining 43
structured search	obtaining command trace records 50
examples of symptoms for RACF 34, 81	obtaining for program access to data sets 44
subsystem dumps	obtaining for program control 44
RACF persistent verification dump title	obtaining on z/OS UNIX System Services 48
description 230	obtaining using SET TRACE command 50
RACF subsystem dump title description 229	transmission and line errors 141
SVC dump title descriptions 224	troubleshooting problems
symptom record 8, 148, 193	overview 1
symptoms	RACF database 107
for a complete search 80	troubleshooting table
for a preliminary search 33	abends incorrectly issued 22
troubleshooting for RACF 8	access with no message issued 20
SYS1.LOGREC entries	DSMON report 23
for callable services errors 193	loop 29
for RRSF errors 148	macro return code or reason code 27
SYS1.MACLIB	messages 21, 29
IRRTEMP2 member 108	overview 7
sysplex data sharing option 3, 126	performance 31
system dump	RACF database 25
formatting 42	RACF LIST command output 23
obtaining 41	reason code from macro or utility 27
	report writer report 23
-	return code from macro or utility 27
T	SMF records 24
tape volume	utility return code or reason code 27
how RACF creates and names profiles 118	
task control block (TCB)	
overview of 224	U
tasks	unloading to a sequential file 121
performing a preliminary search for a matching	UPDATE keyword
problem	on READ subcommand of BLKUPD 127
•	utilities
steps for 33	
SAF keyring debugging	incorrect output 27
steps for 83	IRRBRW00 148
SAF Trace debugging	IRRDBU00 121
steps for 83	process flow 190
using the troubleshooting tables	VSAM file browser 148
steps for 7	
TCB (task control block)	W
overview of 224	V
templates	variable data collected by RACF callable services
description of 107, 108	descriptions 194

VER keyword
on BLKUPD REPLACE subcommand 129
VERIFY request
parameter list 178
VERIFYX request
parameter list 178
VRA (variable recording area) keys
provided by RACF 234
VSAM data sets
IRRBRW00 utility 148
VSAM errors
messages issued 147
VSAM failures 147
automatic direction 147
password synchronization 148

W

waits

example of search argument 37
troubleshooting table 33
worksheet for reporting problems 105
workspace data sets, dumping the data in 148

X

X'0C' delimiter 117 XAPLDIAG parameter 232

Z

z/OS UNIX System Services RACF callable services process flow 193

Readers' Comments — We'd Like to Hear from You

z/OS Security Server RACF Diagnosis Guide

Publication No. GA22-7689-11

We appreciate your comments about this publication. Please comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. The comments you send should pertain to only the information in this manual or product and the way in which the information is presented.

For technical questions and information about products and prices, please contact your IBM branch office, your IBM business partner, or your authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you. IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you state on this form.

Thank you for your support.

Submit your comments using one of these channels:

- · Send your comments to the address on the reverse side of this form.
- Send your comments via e-mail to: mhvrcfs@us.ibm.com

If you would like a response from IBM, please fill in the following information:

Name	Address
Company or Organization	
Phone No.	E-mail address

Readers' Comments — We'd Like to Hear from You GA22-7689-11



Cut or Fold Along Line

Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE NECESSARY IF MAILED IN THE UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation MHVRCFS, Mail Station P181 2455 South Road Poughkeepsie, NY 12601-5400



laalladdalladhaaadlaladalladhaaadll

Fold and Tape

Please do not staple

Fold and Tape

IBM.®

Program Number: 5694-A01

Printed in USA

GA22-7689-11

