IBM TRIRIGA Application Platform Version 3 Release 5.3

# Installation and Implementation Guide



Note Before using this information and the product it supports, read the information in "Notices" on page 99.				

© Copyright IBM Corporation 2011, 2017. US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

### **Contents**

Chapter 1. IBM TRIRIGA Application	Preparing WebLogic
Platform overview 1	Installing IBM TRIRIGA Application Platform
	on WebLogic and Oracle Database 3
Chapter 2. Installing IBM TRIRIGA	Installing IBM TRIRIGA Application Platform
	on WebLogic and Microsoft SQL Server 3
Application Platform 3	Installing IBM TRIRIGA Application Platform
Overview of hardware configuration	on WebLogic and IBM DB2 4
Platform architecture	Installing IBM TRIRIGA Application Platform
Servers 5	with Oracle Database export files 4
Implementations 6	Overview of Oracle Database export
Installing the platform 6	installation 4
Overview of TRIRIGA Application Platform	Installing IBM TRIRIGA Application Platform
installation 6	on WebLogic or WebSphere 4
Before you install IBM TRIRIGA Application	Verification checklist 4
Platform 6	Configuring the platform 4
Types of installation 8	Properties files 5
Installation checklists	TRIRIGAWEB.properties 5
Create and configure a DB2 database for	TRIRIGAWEBDYNAMIC.properties 8
TRIRIGA	TRIRIGAWEBLOGICPOOL.properties 8
Configuring DB2 version 10.5 for TRIRIGA on	TRIRIGADB.properties 8
Windows by using scripts	License files
Configuring DB2 version 10.5 for TRIRIGA on	Before IBM TRIRIGA Application Platform 3.2 8
UNIX and Linux by using scripts 17	IBM TRIRIGA Application Platform 3.2 and
Installing TRIRIGA Application Platform on a	later
WebSphere Application Server Liberty Core	Context path 8
profile	Connection pools 8
Overview of IBM TRIRIGA Application	Cross-site scripting filters 8
Platform installation on a Liberty profile 19	Configuring agent processes 8
Installing TRIRIGA Application Platform on a	Business process agents 8
Liberty profile and Microsoft SQL Server 19	Administrator console
Installing TRIRIGA Application Platform on a	Attaching Microsoft Outlook messages 9
Liberty profile and Oracle Database 21	Configuring the SMTP port in Linux 9
Installing TRIRIGA Application Platform on a	Configuring Tivoli Directory Integrator for IBM
Liberty profile and IBM DB2 23	TRIRIGA
Installing TRIRIGA Application Platform on IBM	Post installation
WebSphere Application Server	
Overview of IBM TRIRIGA Application	Chapter 2 Worldlow eleganus leg 0
Platform installation on WebSphere 26	Chapter 3. Workflow cleanup log 9
Preparing WebSphere 26	Log format
Installing IBM TRIRIGA Application Platform	Reported issues
on WebSphere and Oracle Database 27	Suggested actions
Installing IBM TRIRIGA Application Platform	Automatic repairs 9
on WebSphere and Microsoft SQL Server 29	
Installing TRIRIGA Application Platform on	Notices
WebSphere and IBM DB2	Trademarks
Installing IBM TRIRIGA Application Platform on	Terms and conditions for product documentation 10
Oracle WebLogic Server	IBM Online Privacy Statement
Overview of IBM TRIRIGA Application	
Platform installation on WebLogic	

### Chapter 1. IBM TRIRIGA Application Platform overview

The IBM® TRIRIGA® Application Platform solution provides organizations with graphical and configuration tools to rapidly configure applications and extend the use and value of the IBM TRIRIGA applications. The use of standards-based technology and interfaces and a high-performance workflow process engine drive interoperability with critical business systems.

The IBM TRIRIGA Application Platform is a runtime environment for the rapid processing of transactions. The platform provides the underlying technology for the IBM TRIRIGA applications and includes the Administrator Console, Document Manager, IBM TRIRIGA Connector for Business Applications for integration with external systems, and linkage to computer-aided design (CAD) applications. The IBM TRIRIGA Application Platform also provides set of browser-based tools that are used to create and modify the applications that IBM TRIRIGA delivers.

The IBM TRIRIGA Application Platform includes an MVC-based UX framework for building UX applications. The model-view-controller (MVC) approach separates the application into three components or layers: the model, view, and controller. The view layer is built upon the Polymer library of reusable web components. With a modular and flexible architecture, the UX framework enables organizations to more easily meet business requirements with an intuitive user interface, compatibility with touch interfaces, and improved performance.

With the IBM TRIRIGA comprehensive solution, you can:

- Configure IBM TRIRIGA applications without changing source code.
- Create regulatory reports in the same environment as daily work processes.
- Reduce time and costs to implement and maintain IBM TRIRIGA applications.
- Deliver applications through consistent portals.
- Protect unique configurations through application upgrades.
- Modify an existing business object along with relevant data field definitions, lifecycle states, and workflows.

### **Chapter 2. Installing IBM TRIRIGA Application Platform**

You use the IBM TRIRIGA Application Platform to run, build, and manage the IBM TRIRIGA applications. Installing the platform involves preparing the application and database servers, verifying the installation, configuring the platform settings, and inspecting log reports for installation issues. IBM TRIRIGA Application Platform can be installed on a variety of platforms. Use this installation information to plan and install IBM TRIRIGA Application Platform in the configuration that suits your environment and your needs.

### Overview of hardware configuration

Before you install the IBM TRIRIGA Application Platform, you must determine the platform architecture, server types, and implementation sizes that apply to your business needs.

#### Platform architecture

Enterprise software applications are n-tier, where "n" can represent any number of tiers, or layers of processing. The IBM TRIRIGA Application Platform is a logical four-tier system: web, application (and process), tools, and database.

The layering of an application into logical tiers also separates the functions in each tier. In terms of physical tiers, each physical tier describes the actual hardware configuration, the pieces of equipment, and the function of each piece.




Figure 1. Diagram of the IBM TRIRIGA Application Platform architecture

The *IBM TRIRIGA Application Platform Compatibility Matrix* lists the servers, components, and operating systems on which the *IBM TRIRIGA Application Platform* is certified.

#### Related information:

IBM TRIRIGA Application Platform Compatibility Matrix

#### Servers

The IBM TRIRIGA Application Platform uses many different types of servers. The word "server" is often used to mean a physical piece of equipment, but it can also represent a logical separation that is based on function. Each of these logical servers can be collocated on physical servers, or separated so that each logical tier is installed on their own physical server.

The following logical function-based servers are used in the IBM TRIRIGA Application Platform:

#### Web server

Receives HTTP requests for web content. Also referred to as a front-end server.

#### Application server

Carries out the user business logic with WebLogic Server or WebSphere® Application Server.

#### **Process server**

Carries out the background processing and analytics with WebLogic Server or WebSphere Application Server.

#### Tools server

Carries out the reporting.

#### Database server

Holds the relational database and supported database management system such as Oracle Database, IBM DB2® server, or Microsoft SQL Server.

#### Web server

The web server is the tier with which each user web browser communicates. Examples of web servers include IBM HTTP Server, Microsoft Internet Information Services (IIS), and Apache HTTP Server. The web server handles HTTP requests only and does not run business logic. The IBM TRIRIGA Application Platform also supports Secure Sockets Layer (SSL) by using HTTPS. Typically, HTTP uses port 80 (non-secure connection) and 443 (secure connection), but it can be configured to use other ports. Each time a user requests a JavaServer Page (JSP), the web server passes the request to the application server for processing. The web server is a physical manifestation of the web tier.

#### Application server

The application server is a Java virtual machine (JVM) with an instance of the runtime application. This server runs most of the business logic. Application server processes are CPU-intensive and require a great deal of memory. The application tier consists of JavaServer Pages (JSP) and Java classes. The Java™ 2 Platform, Enterprise Edition (J2EE) application server provides a JSP container, a database connection pool, and transaction management services. The application server is a physical manifestation of the application (middleware) tier.

#### **Process server**

The process server is a JVM with an instance of the runtime application that is set up as a dedicated processing or analytics engine. This server is configured almost exactly like an application server, but no users sign on to this server. It handles all workflow requests that are queued from users or by the IBM TRIRIGA software. The process server is a physical manifestation of the application (middleware) tier.

#### Tools server

The tools server houses the third-party extensions from IBM TRIRIGA. You can designate a IBM TRIRIGA application server as a BIRT process server. If you choose to run both BIRT and IBM TRIRIGA on the same server, expect BIRT report handling operations to increase the load on the server. BIRT is run in the same JVM as IBM TRIRIGA in all cases.

#### **Database server**

The database server runs the database process. The database is where data is stored. The major database servers use Structured Query Language (SQL) to store and retrieve data. The Oracle Database server, IBM DB2 server, and Microsoft SQL Server use SQL. But each server is a different database engine and each has its own extended SQL for competitive differentiation. The application tier communicates with the database tier by using JDBC connection pools. The database server is a physical manifestation of the database tier.

### **Implementations**

The physical configuration of any system depends greatly on the number of users and amount of data that it supports. For information about IBM TRIRIGA Application Platform system implementations, see the IBM TRIRIGA Best Practices for System Performance.

Before you deploy IBM TRIRIGA in your organization, plan how the user community should access TRIRIGA applications. IBM TRIRIGA requires a user name and password to gain access to applications. Refer to the IBM TRIRIGA Application Platform 3 Single Sign-On Setup User Guide if you want to configure single sign-on (SSO) to manage user access to TRIRIGA applications.

#### Related information:



Best Practices for System Performance

### Installing the platform

You can select the IBM TRIRIGA Application Platform installation process that applies to your hardware configuration, whether you have a Oracle WebLogic Server or IBM WebSphere Application Server. For added flexibility, you can also install the platform with Oracle Database export files.

### Overview of TRIRIGA Application Platform installation

After you determine the platform architecture, server types, and implementation sizes that apply to your business needs, you are ready to install the TRIRIGA Application Platform.

#### Before you install IBM TRIRIGA Application Platform

Verify IBM TRIRIGA Application Platform hardware and software requirements before you start the installation process.

The IBM TRIRIGA Application Platform Compatibility Matrix provides information about the IBM TRIRIGA supported software products. It lists the application servers, database servers, web servers, third-party servers, third-party components, and client options with which the IBM TRIRIGA Application Platform is certified.

Refer to the IBM TRIRIGA Application Platform 3.4.x Best Practices for System Performance guide for extensive system performance information.

Furthermore, the following list outlines the hardware requirements and other software considerations:

#### Memory

The database server must have at least 3 GB of physical dedicated memory.

Ensure that you allocate enough memory to your application servers. Monitor memory usage regularly to avoid out of memory errors. You might also want to consider deploying a second process server to ensure that workflow processing continues if a process server experiences a failure.

#### Disk space

You must prepare the following disk space requirements:

- If you download all components of an installation, you need at least 1.8 GB of disk space.
- In addition, the installation occupies approximately 300 MB of disk
- For the installer to run, you need at least 160 MB in temporary space on the hard disk.
- For a new installation, you need at least 7 GB within the database.
- Each WebSphere Application Server profile requires approximately 1 GB of disk space.

#### Application server and database server

The application server and database server must be in the same physical location, such as a room or building to avoid issues with network latency. Minimize the number of segments or along the path between the application server and the database server. The minimum network speed that is required is fast Ethernet (100 Mbps), switched.

#### Application server software

The WebLogic Server or WebSphere Application Server software must be installed before you run the IBM TRIRIGA Application Platform installer. The only supported method of configuring WebLogic Server or WebSphere Application Server is to allow the TRIRIGA Application Platform installer to run the setup tasks.

If the value set for the maximum number of parameters allowed in an inbound request is too low, an error can occur when saving a workflow object map. In this case, you can either increase the value, or set the value to unlimited. Refer to the product documentation for your application server for details.

#### Database server software

Oracle Database, IBM DB2, or Microsoft SQL Server must be installed before you run the IBM TRIRIGA Application Platform installer. During the installation process, you are required to provide the database administrator (DBA) user ID and password.

#### Oracle Database installations

Table spaces for new Oracle Database installations must be created before you run the installer. Analyze your base data. This data includes documents, leases, and portfolio data, such as people, organizations, assets, and locations. Set the sizes for the TRIDATA\_DATA table space and TRIDATA\_INDX table space to support at least this base data. The

minimum size for the TRIDATA\_DATA table space and TRIDATA\_INDX table space is 2.5 GB each. If you use existing IBM TRIRIGA table spaces, verify that the autoextend option is enabled.

#### IBM DB2 installations

An IBM DB2 instance and database must be created before you run the IBM TRIRIGA Application Platform installer.

#### Java Development Kit

The Java Development Kit (JDK) must be installed before you run the IBM TRIRIGA Application Platform installer. The JDK must be installed before you run the IBM TRIRIGA application. Java must be running during an IBM TRIRIGA Application Platform installation. You must set the JAVA\_HOME environment variable to the path of the JDK before you start the IBM TRIRIGA Application Platform installation program.

GNU OpenJDK is not supported and will not work with IBM TRIRIGA and the IBM TRIRIGA Application Platform installation program. The OpenJDK package should be completely uninstalled from the server.

#### Security privileges and directory access

The administrator or user who runs the IBM TRIRIGA Application Platform installation must have create access and write access to the installation root directory.

#### IBM TRIRIGA licenses (keys)

Starting with IBM TRIRIGA Application Platform version 3.2, IBM TRIRIGA distributes software licenses in a separate license file for each product. The license file names are in the format LICENSE\_IBM\_TRIRIGA\_[productname].properties (for example, LICENSE\_IBM\_TRIRIGA\_Application\_Platform.properties). You can continue to use an existing TRIRIGALICENSE.properties file if you have one until it expires or you use a new product. For more information, see the topic about license files.

#### Related concepts:

"Create and configure a DB2 database for TRIRIGA" on page 15 To configure TRIRIGA with DB2 version 10.5, you must create a database before you start the TRIRIGA Application Platform installation program. You can either create the database manually, or, you can use scripts that are provided with TRIRIGA.

#### Related information:

IBM TRIRIGA Application Platform Compatibility Matrix

#### Types of installation

Before you install the IBM TRIRIGA Application Platform, determine the installation path that applies to your particular implementation. Although there are several installation paths, they follow the same general installation process. These installation types include full installation and database-only installation. Full installations install and configure all key components for IBM TRIRIGA, including the application server. Database-only installations create the database without installing the application server.

#### Installation preparation

Whether you choose a full installation or database-only installation, prepare the following access and information before you begin:

For Oracle Database, the system identification (SID) or database instance name

- For Microsoft SQL Server, the database name
- For IBM DB2, the instance port and database name
- For existing databases, the database instance login information
- · Server name and IP address of the database server
- Server name of the process server

The process of installing IBM TRIRIGA is the same regardless of the level of security that is applied to your environment. After installation, you can secure your environments according to your business requirements. For instance, security considerations might include securing client communication and restricting access to servers.




Figure 2. Flow diagram for the general IBM TRIRIGA installation process

#### Full installation process

A full installation process includes installing the key components and configurations necessary for the IBM TRIRIGA platform and applications to operate:

- Application server
- Database scripts
- Database




Figure 3. Flow diagram for the full IBM TRIRIGA installation process

#### **Database-only installation process**

A database-only installation process creates the database without installing the application server. Do not select the database-only installation or upgrade unless you are directed to do so by the team responsible for planning the IBM TRIRIGA deployment. If you install the database now and you install a newer version of the application server later, an incompatibility can occur between a new feature and the database.




Figure 4. Flow diagram for the database-only IBM TRIRIGA installation process

#### **Installation checklists**

Before you install the IBM TRIRIGA Application Platform, you can follow the application server and database checklists that apply to your implementation.

#### **Checklist for new IBM TRIRIGA Application Platform installations**

Item	Description
Release notes	Read the <i>IBM TRIRIGA Release Notes</i> that apply to your installation version for information and instructions that are specific to that release.

Item	Description
Data recovery and backups	Before starting the installation process, create a data recovery plan to be used in the event of a IBM TRIRIGA Application Platform system failure. IBM TRIRIGA is a Java enterprise application that runs on a variety of Java application servers and database platforms. Each application server and database platform provides different methods and recommendations for backups and recovery. Consult the product information provided with the application server and database platform you are using with IBM TRIRIGA for backup and recovery operation standards and best practices. After a successful installation, the IBM TRIRIGA installation folder can be backed up regularly to preserve IBM TRIRIGA system settings.
Full installation	Follow the full installation process for a new installation. If you are upgrading an existing IBM TRIRIGA implementation, see the IBM TRIRIGA Application Platform 3 Upgrade Installation Guide.
Language packs	To decrease the size of the IBM TRIRIGA Application Platform installer, the installer no longer includes the IBM TRIRIGA language packs .zip file. The language packs .zip file is on the Application Upgrade image in the IBM TRIRIGA application eAssembly on the IBM Passport Advantage website. Download the image and copy the language packs .zip file into the <code>[install directory]</code> \userfiles\LanguagePacks directory on your TRIRIGA server. The directory structure of the language packs separates the label packs from the data packs. You must unpack the main language pack before you select the individual language pack to import. Make sure that you import the correct type of language pack in the specific interface. For example, if you are in the Label Manager, you must import a label pack. If you are in the Language Manager, you must import a data pack. Importing a data pack is not required if your installation is US English only. For more information, see the IBM TRIRIGA Application Platform 3 Localization User Guide.
First steps in the installation	<ul> <li>Install the 64-bit version of IBM Java 8. The Java installation path must not contain spaces.</li> <li>Run the installer:         <ul> <li>From the Windows environment, double-click the install.exe file. On Windows, C:\Tririga is the default installation location.</li> <li>Connect and log in to your application server as the IBM TRIRIGA user through SSH or other remote terminal application.</li> </ul> </li> <li>From the UNIX or Linux command line, log in to a terminal as the IBM TRIRIGA user and type</li></ul>
	After the root super user pre-creates this directory, run the chown tririga /usr/local/tririga command as root, where tririga is the name of the installation user.

Item	Description
Java virtual machine	During the installation:
(JVM)	• Select the path to the Java virtual machine (JVM) that you want the installer to use. The screen lists the java.exe versions that are available on your target computer. IBM TRIRIGA supports the 64-bit version of IBM Java 8 only.
	WebSphere Application Server installations support 64the -bit version of IBM Java 8. WebLogic Server installations support Oracle Java.
	• If you see the following message, "Unable to install the Java Virtual Machine included with this installer", then continue with the installation. This message is caused by the version of InstallAnywhere that is used by the installer. It has no effect on the installation.
Installation directory	During the installation, specify the complete path of the directory to which you want to install the files:
	• The installation path must not have any spaces. If it has spaces, specify another path. On Windows, C:\Tririga is the typical location. On UNIX, /usr/local/tririga is the typical location.
	• The directory must not have an existing installation. If it has an existing installation, rename that directory. For example, rename the directory to add the word "old" and the date.
Application data	During the installation, choose the compressed file where the IBM TRIRIGA application data is stored. This compressed file is named data.zip and is selected automatically by the installer. If the file is not selected, then locate and select the correct file.
After the installation	After the installation is complete:
	Verify that your installation is running properly. For more information, see the topic about the verification checklist.

# Checklist for new IBM TRIRIGA Application Platform installations on Oracle Database

Item	Description
Release notes	Read the IBM TRIRIGA Release Notes.
Multibyte language support	If you support multibyte languages, the Oracle Database must originally be installed as a multibyte database. If the database was not originally installed as a multibyte database, it cannot be changed afterwards.
Multibyte language support	If you support multibyte languages, take the following steps before you begin the installation:
	• Set the instance character set to UTF-8 or UTF-16. If you do not select a UTF-8 or UTF-16 character set, a multibyte character is shown as a question mark when saved in the database.
	Set the NLS_LENGTH_SEMANTICS parameter to CHAR (not BYTE). If you use BYTE instead of CHAR, the platform does not run the length operations correctly and data can be lost.
	Set a block size of at least 16K.
User name requirement	For Oracle Database, the schema owner must use the same user ID as the database user.

# Checklist for new IBM TRIRIGA Application Platform installations on Microsoft SQL Server

Item	Description	
Release notes	Read the IBM TRIRIGA Release Notes.	
Users	Verify that the database user that is being used for the new installation is uniquely associated to the database.	
Multibyte language support	New installations of IBM TRIRIGA only support Microsoft SQL Server databases configured for multibyte languages. You must select a collation for the database when you install IBM TRIRIGA.	
Multibyte language support and WebLogic Server	Verify on the WebLogic Server that the JDBC URL in your DataSource-TRIRIGA-data sets the property of SendStringParametersAsUnicode to true.	
Multibyte language support and WebSphere Application Server	Verify in the WebSphere Application Server data source that the custom property of <b>sendStringParametersAsUnicode</b> is set to true.	
User name requirement	You can use different Microsoft SQL Server values for the database name and the database user ID.	
Database authentication	For Microsoft SQL Server, the database login is required to be SQL Server Authentication. Windows authentication is not supported. In addition, this account must be the DBO of the database, and have full permissions to all functions and methods to allow IBM TRIRIGA Application Platform to function.	
Database collation and case-sensitivity.	You can install IBM TRIRIGA on a Case Sensitive Microsoft SQL Server, however, the TRIRIGA database must be Case Insensitive.	

# **Checklist for new IBM TRIRIGA Application Platform installations on IBM DB2**

Item	Description	
Release notes	Read the IBM TRIRIGA Release Notes.	
IBM DB2	Perform DB2 configuration steps.	
Multibyte language support	If you support multibyte languages, the IBM DB2 database must originally be created as UTF-8. If the database was not originally created as UTF-8, it cannot be changed afterwards.	
	Set the string_units parameter to CODEUNITS32.	
Data collection performance settings in WebLogic Server.	Data collection performance settings are configured with data source properties using the following parameter values: user=TRIRIGA DB User DatabaseName=DB Name jdbcCollection=NULLIDR1	
Data collection performance settings in WebSphere Application Server.	Data collection performance settings are configured by adding a new property to the data source properties: jdbcCollection=NULLIDR1  The isolation level for WebSphere Application Server is set to webSphereDefaultIsolationLevel=2 to prevent database locking.	

#### Related information:

- IBM TRIRIGA Application Platform 3 Upgrade Installation Guide

### Create and configure a DB2 database for TRIRIGA

To configure TRIRIGA with DB2 version 10.5, you must create a database before you start the TRIRIGA Application Platform installation program. You can either create the database manually, or, you can use scripts that are provided with TRIRIGA.

Configuring an existing DB2 version 10.5 server for use with TRIRIGA involves several steps. You must create a TRIRIGA user, create a database, and configure instance and database level settings before you start the IBM TRIRIGA Application Platform installation program. You can create these database objects by using scripts that are provided with TRIRIGA. Scripts for Windows, Linux, and UNIX are provided in the IBM TRIRIGA Application Upgrade V10.5 Multiplatform Multilingual package. The script files are located in the Scripts directory of the TRI\_APPLICATION\_UPGRADE\_10.5.zip archive file.

If you create the database objects manually, refer to the scripts for configuration values. You can specify your own values when you create the users, name the database and instance, and define the port that is used by the TRIRIGA database instance. You must accurately provide the DB2 installation directory.

The DB2 database used with TRIRIGA must be configured with the following parameters.

- The DB2 database instance and database must be set to Oracle mode.
- DB2 database parameters must be configured to optimize TRIRIGA performance.
  - STMT CONC=OFF
  - PAGESIZE=32 K
  - DB2 DEFERRED PREPARE SEMANTICS=YES
- The user ID created for TRIRIGA to access the database must have DBADM, SECADM, ACCESSCTRL and DATAACCESS privileges for the database.
- The database must be configured with the UTF-8 code set and CODEUNITS32 string unit if you need to support multibyte characters.

The DB2 port used to communicate with TRIRIGA needs to be available through any firewall software that is active on the system. You can disable firewall software on the DB2 server before you run the TRIRIGA database creation scripts. Firewall software can prevent the TRIRIGA scripts from completing successfully. You can reactivate the firewall after the database is created.

### Configuring DB2 version 10.5 for TRIRIGA on Windows by using scripts

Use the db2createinst and db2createdb commands to create and configure a DB2 database on Windows.

#### **Procedure**

1. Log in to the server that is running DB2 version 10 as a user that has administrative permissions on the system.

- 2. Create a system user for TRIRIGA, for example, tridata. This system user is used by TRIRIGA to access the database. This user is given permission to access the database by the scripts.
- 3. Log in to the server as the DB2 administrative user. The default user ID for the DB2 administrative user is db2admin.
- 4. Create the DB2 instance and set it to Oracle Compatibility mode.
  - a. Copy the db2createinst.cmd command file from \scripts in the installation media to a temporary directory on the DB2 server.
  - b. Open a DB2 command window and run the db2cmdadmin command to set up the DB2 environment:
    - Alternatively, you can use Start > DB2 Command Window -Administrator.
  - c. Run the **db2createinst** command to create and configure the database instance.

```
db2createinst name port installDir
db2admin password > outputfilename
```

The **name** parameter specifies the DB2 instance name. The **port** parameter specifies the server port that is used by this instance of DB2. The installDir parameter specifies the installation location of DB2. You must use double quotation marks around the value if the path contains spaces. The **db2admin** parameter specifies the DB2 administrator. The outputfilename parameter specifies the file that is used to capture output from the command. The following example provides sample syntax for the db2createinst command.

```
C:\temp>db2createinst triinst 50006
"c:\program files\ibm\sqllib"
db2admin mypassword > db2createinst.log
```

If the command generates an instance creation return code of 0, the DB2 database instance is created and set to Oracle Compatibility mode, and the message Instance instance name has been created successfully and started on port port number is displayed. If the command generated any return codes other than 0, examine the output of the command to determine the cause of the error. You can capture the output of the script to a file to evaluate the command results. Do not attempt to create the database until the db2createinst command completes successfully.

- 5. Create and configure the DB2 database.
  - a. Copy the db2createdb.cmd command file from \scripts in the installation media to a temporary directory on the DB2 server.
  - b. Start the **db2createdb** command from the DB2 command window.

db2createdb name instance territory installDir tririgaUser db2admin > outputfilename

The name parameter specifies the name of the database. The instance parameter specifies the instance that is associated with the database. The **territory** parameter designates the code that is used by the database manager internally to provide region-specific support. The **installDir** parameter specifies the installation location of DB2. You must use double quotation marks around the value if the path contains spaces. The tririgalser parameter specifies the TRIRIGA user ID that is used to access the database. The **db2admin** parameter specifies the DB2 administrator user

ID. The **outputfilename** parameter specifies the file that is used to capture output from the command. The following example provides sample syntax for the **db2createdb** command.

```
C:\temp>db2createdb tririga triinst
US "c:\Program files\ibm\sqllib"
tridata db2admin > db2createdb.log
```

If the command generates an exit return code of 0, the DB2 database is created and configured, and the message Database database name has been created successfully on instance name. is displayed. If the command generated any exit codes other than 0, examine the output of the command to determine the cause of the error. You can capture the output of the script to a file to evaluate the command results. Do not continue with the IBM TRIRIGA Application Platform installation process until the db2createdb command completes successfully.

#### What to do next

If you have a firewall, reactivate it and make sure remote connections can be made to the database. Use IBM Data Studio or another SQL tool to verify that a remote connection can be made to the database before you start the IBM TRIRIGA Application Platform installation program. You may need to allow access to the port used by DB2 in the firewall.

## Configuring DB2 version 10.5 for TRIRIGA on UNIX and Linux by using scripts

Use the **db2createinst**, **db2configinst**, and **db2createdb** commands to create and configure a DB2 database on UNIX or Linux.

- 1. Log in to the server that is running DB2 version 10 as a user that has administrative permissions on the system. The user must be able to create system users and DB2 instances.
- 2. Create system users for TRIRIGA.
  - a. Create a system user for TRIRIGA to access the database, for example, tridata. This user is given permission to access to the database by the scripts.
  - b. Create the DB2 instance owner, for example triinst. The DB2 instance owner creates the DB2 instance for TRIRIGA. This user must not have any existing DB2 instances associated with it. The triinst user ID must be assigned to the db2iadm1 group.
  - c. Create the fenced user ID for the DB2 instance, for example, db2fenc1. This user ID might already exist on the system and can serve as the fenced user ID for other DB2 instances. The db2fenc1 user ID must be assigned to the db2iadm1 group.
- 3. Create the DB2 database instance.
  - a. Copy the db2createinst.sh command file from /Scripts in the installation media to a temporary directory on the DB2 server.
  - b. Ensure the user ID has execute privileges on the file and write privileges to the current directory.
  - c. Open a shell window and run the **db2createinst** command to create the database instance.

```
db2createinst.sh name port
installDir fenceUser
> outputfilename
```

The name parameter specifies the DB2 instance owner. The port parameter specifies the server port that is used by this instance of DB2. The <code>installDir</code> parameter specifies the installation location of DB2. The <code>fenceUser</code> parameter specifies the DB2 fence user. The <code>outputfilename</code> parameter specifies the file that is used to capture output from the command. The following example provides sample syntax for the <code>db2createinst</code> command.

```
./db2createinst.sh triinst 50006
/opt/ibm/db2/V10.5
db2fenc1 > db2createinst.log
```

If the command generates an instance creation return code of 0, the DB2 database instance is created, and the message Instance *instance name* has been created successfully on port *port number* is displayed. If the command generated any return codes other than 0, examine the output of the command to determine the cause of the error. You can capture the output of the script to a file to evaluate the command results. Do not attempt to configure the database instance until the **db2createinst** command completes successfully.

- 4. Log in to the server that is running DB2 version 10 as the instance user.
- 5. Configure the DB2 database instance.
  - a. Copy the db2configinst.sh command file from /scripts in the installation media to a temporary directory on the DB2 server.
  - b. Ensure the user ID has execute privileges on the file and write privileges to the current directory.
  - c. From the shell window, run the db2configinst command to create the database instance.

```
db2configinst.sh name port installDir > outputfilename
```

The name parameter specifies the DB2 instance to configure. The port parameter specifies the server port that is used by this instance of DB2. The <code>installDir</code> parameter specifies the installation location of DB2. The <code>outputfilename</code> parameter specifies the file that is used to capture output from the command. The following example provides sample syntax for the <code>db2configinst</code> command.

```
./db2configinst.sh triinst 50006
/opt/ibm/db2/V10.5
> db2configinst.log
```

If the command generates a return code for starting instance of 0, the DB2 database instance is created, and the message Instance *instance name* has been configured successfully and started on *server name* is displayed. If the command generated any return codes other than 0, examine the output of the command to determine the cause of the error. You can capture the output of the script to a file to evaluate the command results. Do not attempt to create the database until the **db2configinst** command completes successfully.

- 6. Create and configure the DB2 database.
  - a. Copy the db2createdb.sh command file from /scripts in the installation media to a temporary directory on the DB2 server.
  - b. Ensure the user ID has execute privileges on the file and write privileges to the current directory.
  - **c**. From the shell window, run the **db2createdb** command.

```
db2createdb.sh name instance territory
installDir tririgaUser > outputfilename
```

The name parameter specifies the name of the database. The instance parameter specifies the instance that is associated with the database. The territory parameter designates the code that is used by the database manager internally to provide region-specific support. The installDir parameter specifies the installation location of DB2. The tririgaUser parameter specifies the TRIRIGA user ID used to access the database. The outputfilename parameter specifies the file that is used to capture output from the command. The following example provides sample syntax for the db2createdb command.

./db2createdb.sh tririga
triinst US /opt/ibm/db2/V10.5
tridata > db2createdb.log

If the command generates an exit return code of 0, the DB2 database is created and configured, and the message Database database name has been created successfully on instance name is displayed. If the command generated any return codes other than 0, examine the output of the command to determine the cause of the error. You can capture the output of the script to a file to evaluate the command results. Do not continue with the IBM TRIRIGA Application Platform installation process until the db2createdb command completes successfully.

#### What to do next

If you have a firewall, reactivate it and make sure remote connections can be made to the database. Use IBM Data Studio or another SQL tool to verify that a remote connection can be made to the database before you start the IBM TRIRIGA Application Platform installation program. You may need to allow access to the port used by DB2 in the firewall.

# Installing TRIRIGA Application Platform on a WebSphere Application Server Liberty Core profile

TRIRIGA Application Platform can be installed on a Liberty profile and supported by a variety of database software. During the TRIRIGA Application Platform installation process, you can select the type of application server you want to use.

#### Before you begin

Check the IBM TRIRIGA product wiki for the latest information about deploying IBM TRIRIGA on a Liberty profile.

IBM TRIRIGA application data must be stored on the same filesystem as the filesystem used by the Liberty profile host.

## Overview of IBM TRIRIGA Application Platform installation on a Liberty profile

Liberty profiles are dynamic and provision only the features needed by the application, which contributes to faster load speed and a smaller footprint.

The IBM TRIRIGA Application Platform installation program installs the Liberty profile components during the installation process.

## Installing TRIRIGA Application Platform on a Liberty profile and Microsoft SQL Server

After your database server is prepared, you can begin to install the TRIRIGA Application Platform on a Liberty profile and Microsoft SQL Server.

#### Before you begin

Verify that Microsoft SQL Server is running and that you have administrative authority on the server. Ensure the Microsoft SQL Server database has been configured for TRIRIGA.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - c. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select **New Database (data.zip required)** and then select the data file to install.
- 2. Select the data file to install and click **Choose**.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **IBM WebSphere Liberty (Embedded)**. Specify the Liberty profile information in the next set of screens.
  - a. Specify the Java memory setting values in megabytes.
  - b. Specify HTTP and HTTPS ports and the session timeout value used by the Liberty Profile.
  - c. Optional: Configure TRIRIGA to run Liberty as a Windows service. You must run the TRIRIGA installation program as an Administrator to create the Windows service. If you did not run the TRIRIGA installation program as an Administrator, quit the installation program and restart it with Administrator privileges. This service will replace an existing Liberty Windows service on the system unless you assign it a unique service name.
  - d. Specify the application context root for accessing the IBM TRIRIGA application. This path must begin with a slash (/).
- 5. For the database type, select **Microsoft SQL Server**. Consult with your Microsoft SQL Server administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces, creating the schema, and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. When you create the database, you must load data using the installation program.
  - b. Specify the information for the database server connection, such as the port and name. For example, 1433 is a typical value for the Microsoft SQL Server port, and tridata is a typical value for the Microsoft SQL Server database name.
  - **c.** Specify the database user name and password. For example, tridata is a typical value for both fields. Verify that the database user that is being used for the new installation is uniquely associated to the database.
  - d. Choose a collation for the Microsoft SQL Server database.
  - Specify the database administrator user name and password. This
    information is required to set up the database structures and schema

- owner. You are not prompted to specify the database administrator user if you chose to load the database from a .zip file as the only database action to perform.
- f. Review the URL that the installer is using to test the data schema connection.
- g. Review the results of the test. If the test fails, verify that Microsoft SQL Server is running.
- h. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click **Install**.

#### 7. Click Next.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. When the installation is complete, click **Done**.
- 9. Confirm that your license files are in the <code>tririga\_root</code>\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 10. Restart IBM TRIRIGA using the appropriate method.
  - On Windows servers, open a command prompt and run the command to start the Liberty profile. tririga root\wlp\bin\run.bat
  - On UNIX servers, open a command prompt and run the command to start the Liberty profile. tririga\_root/wlp/bin/run.sh

The command window closes after initial startup. Liberty continues to run as a background process.

#### What to do next

Verify that your installation is running properly.

## Installing TRIRIGA Application Platform on a Liberty profile and Oracle Database

After your database server is prepared, you can begin to install the TRIRIGA Application Platform on a Liberty profile and Oracle Database.

#### Before you begin

Verify that Oracle Database is running and that you have administrative authority on the server. Ensure the Oracle Database database instance and the database have been configured for TRIRIGA.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - c. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select New Database (data.zip required) and then select the data file to install.
- 2. Select the data file to install and click Choose.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **IBM WebSphere Liberty (Embedded)**. Specify the Liberty profile information in the next set of screens.
  - a. Specify the Java memory setting values in megabytes.
  - b. Specify HTTP and HTTPS ports and the session timeout value used by the Liberty Profile.
  - c. Optional: Configure TRIRIGA to run Liberty as a Windows service. You must run the TRIRIGA installation program as an Administrator to create the Windows service. If you did not run the TRIRIGA installation program as an Administrator, quit the installation program and restart it with Administrator privileges. This service will replace an existing Liberty Windows service on the system unless you assign it a unique service name.
  - d. Specify the application context root for accessing the IBM TRIRIGA application. This path must begin with a slash (/).
- 5. For the database type, select **Oracle**. Consult with your Oracle Database administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces, creating the schema, and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. When you create the database, you must load data using the installation program.
  - b. Specify the information for the data schema database server, such as the host name, port, and system identification (SID). For example, 1521 is a typical value for the Oracle Database server port, and orcl is a typical value for the Oracle Database server system identification.
  - c. Specify the data schema user name and password. For example, tridata is a typical value for both fields.
  - d. Specify the names of the data schema table spaces. Only letters and the underscore can be used in the table space name. For example, TRIDATA DATA is a typical value for data and TRIDATA INDX is a typical value for indexes.
  - e. Optional: Specify the data schema table space parameters, such as the file names and file sizes in megabytes. This screen is displayed if you chose to create the table spaces. The default file size is 2500 MB (or 2.5 GB), which is the minimum that is required. To determine the correct size of these files, conduct a careful analysis. If the autoextend option is enabled for table spaces within the database, the table spaces are automatically extended as needed. However, this extension might severely affect performance.

- f. Optional: Specify the database administrator user name and password. This screen is displayed if you chose to create the table spaces and schema. This information is required to set up the database structures and schema owner. You are not prompted to specify the database administrator user if you chose to load the database from a .zip file as the only database action to perform.
- g. Review the URL that the installer is using to test the data schema connection.
- h. Review the results of the test. If the test fails, verify that Oracle Database is running. If you see an informative message that your database might not properly support multibyte characters and your implementation must support multibyte characters, then click **Cancel**. Adjust your database and restart the installer.
- i. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click Install.

#### 7. Click Next.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. When the installation is complete, click **Done**.
- 9. Confirm that your license files are in the <code>tririga\_root</code>\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 10. Restart IBM TRIRIGA using the appropriate method.
  - On Windows servers, open a command prompt and run the command to start the Liberty profile. <a href="mailto:tririga\_root">tririga\_root</a> \wlp\bin\run.bat
  - On UNIX servers, open a command prompt and run the command to start the Liberty profile. *tririga root*/wlp/bin/run.sh

The command window closes after initial startup. Liberty continues to run as a background process.

#### What to do next

Verify that your installation is running properly.

### Installing TRIRIGA Application Platform on a Liberty profile and IBM DB2

After your database server is prepared, you can begin to install the TRIRIGA Application Platform on a Liberty profile and IBM DB2.

#### Before you begin

Verify that IBM DB2 is running and that you have administrative authority on the server. Ensure the IBM DB2 database instance and the database have been configured for TRIRIGA.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - c. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select **New Database (data.zip required)** and then select the data file to install.
- 2. Select the data file to install and click **Choose**.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **IBM WebSphere Liberty (Embedded)**. Specify the Liberty profile information in the next set of screens.
  - a. Specify the Java memory setting values in megabytes.
  - b. Specify HTTP and HTTPS ports and the session timeout value used by the Liberty Profile.
  - c. Optional: Configure TRIRIGA to run Liberty as a Windows service. You must run the TRIRIGA installation program as an Administrator to create the Windows service. If you did not run the TRIRIGA installation program as an Administrator, quit the installation program and restart it with Administrator privileges. This service will replace an existing Liberty Windows service on the system unless you assign it a unique service name.
  - d. Specify the application context root for accessing the IBM TRIRIGA application. This path must begin with a slash (/).
- 5. For the database type, select **IBM DB2**. Consult with your IBM DB2 administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. For example, if your database administrator pre-created the table space, clear the first option. When you create the database, you must load data using the installation program.
  - b. Specify the information for the data schema database server, such as the host name, port, and database name. For example, 50006 is a typical value for the IBM DB2 server port, and tririga is a typical value for the IBM DB2 database name.
  - **c.** Specify the IBM TRIRIGA database user name and password. For example, tridata is a typical value for the database user name.
  - d. Specify the names of the data schema table spaces. Only letters and the underscore can be used in the table space name. For example, TRIDATA\_DATA is a typical value for data and TRIDATA\_INDX is a typical value for indexes.

- e. Review the URL that the installer is using to test the data schema connection.
- f. Review the results of the test. If the test fails, verify that IBM DB2 is running. If you see an informative message that your database might not properly support multibyte characters and your implementation must support multibyte characters, then click Cancel. Adjust your database and restart the installer. For the IBM TRIRIGA Application Platform to work correctly, the instance must be configured to use Oracle compatibility mode. To support multibyte characters, the codeset of the IBM DB2 instance must support UTF-8 and string\_units must be set to CODEUNITS32.
- g. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click Install.

#### 7. Click Next.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. When the installation is complete, click **Done**.
- 9. Confirm that your license files are in the <code>tririga\_root</code>\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 10. Restart IBM TRIRIGA using the appropriate method.
  - On Windows servers, open a command prompt and run the command to start the Liberty profile. <a href="mailto:tririga\_root">tririga\_root</a> \wlp\bin\run.bat
  - On UNIX servers, open a command prompt and run the command to start the Liberty profile. tririga\_root/wlp/bin/run.sh

The command window closes after initial startup. Liberty continues to run as a background process.

#### What to do next

Verify that your installation is running properly.

# Installing TRIRIGA Application Platform on IBM WebSphere Application Server

TRIRIGA Application Platform can be installed on IBM WebSphere Application Server and supported by a variety of database software. During the TRIRIGA Application Platform installation process, you can select the type of application server you want to use.

#### Before you begin

Check the IBM TRIRIGA product wiki for the latest information about deploying IBM TRIRIGA on IBM WebSphere Application Server.

IBM TRIRIGA can be installed on IBM WebSphere Application Server Network Deployment, but it does not support deployment into clustered environments. You must install IBM TRIRIGA on the default application server of a single Cell containing a single Node within IBM WebSphere Application Server Network Deployment. IBM TRIRIGA application data must be stored on the same filesystem as the filesystem used by the IBM WebSphere Application Server host. IBM TRIRIGA can be configured for high availability through the use of IBM WebSphere Application Server sticky sessions.

## Overview of IBM TRIRIGA Application Platform installation on WebSphere

Before you begin the IBM TRIRIGA Application Platform installation, IBM WebSphere Application Server must be installed locally or on a server.

#### Installation phases

Installing the platform on the WebSphere Application Server involves several phases:

- Create a WebSphere Application Server profile for IBM TRIRIGA. If you do not create a new WebSphere Application Server profile specifically for IBM TRIRIGA, you must be prepared to specify information about an existing profile to use with IBM TRIRIGA during the installation process.
- Using IBM Installation Manager, update WebSphere Application Server to v 8.5.5.9. Also using Installation Manager, install IBM Java 8 64 bit. See http://www-01.ibm.com/support/docview.wss?uid=swg24041819 for more information
- Running the IBM TRIRIGA installation.

#### Preparing WebSphere

A WebSphere Application Server profile is required to install IBM TRIRIGA. You can create a WebSphere Application Server profile specifically for IBM TRIRIGA if you do not want to use the default profile. If you do not create a new WebSphere Application Server profile, you must be prepared to specify information about an existing WebSphere Application Server profile to use with IBM TRIRIGA during the installation process. Refer to WebSphere Application Server product information for details about creating profiles.

#### **Procedure**

1. Enable all WebSphere Application Server profiles to use IBM Java 8.

/QIBM/ProdData/WebSphere/AppServer /version/edition/bin/managesdk -enableProfileAll -sdkname 1.8\_64 -enableServers

2. Set the SDK name that script commands are enabled to use when no profile is specified by the command and when no profile is defaulted by the command.

/QIBM/ProdData/WebSphere/AppServer /version/edition/bin/managesdk -setCommandDefault -sdkname 1.8 64

- 3. Update the location of the /tmp directory to use, if required. The /tmp directory should be at least 2GB in size.
  - a. Navigate to Servers > Application Servers > server1 > Java and Process
     Management > Process Definition > Java Virtual Machine > Custom
     Properties.
  - b. Click **New**, and enter the following properties.

Name: java.io.tmpdir Value: /path/to/new/tmpdir

Description: Path to desired temp directory

c. Click **OK** and then **Save**.

#### What to do next

Install the platform with the Oracle Database, IBM DB2, or Microsoft SQL Server.

## Installing IBM TRIRIGA Application Platform on WebSphere and Oracle Database

After your application server and database server are prepared, you can begin to install the IBM TRIRIGA Application Platform on IBM WebSphere Application Server and Oracle Database.

#### Before you begin

Verify that the Oracle Database and IBM WebSphere Application Server are running and that you have administrative authority on the servers.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - **c**. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select **New Database (data.zip required)** and then select the data file to install.
- 2. Select the data file to install and click Choose.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **IBM WebSphere Application Server** (**Standalone**). Specify the WebSphere Application Server information in the next set of screens.
  - a. Specify the information for the WebSphere Application Server configuration, such as the cell, node, server, profile, and home. Log on to the WebSphere Application Server and run the manageprofiles. [bat|sh] —listProfiles command to identify the cell, node, server, profile, and home values. WebSphere Application Server home is defined as C:\Program Files\IBM\WebSphere\AppServer, for example. Copy values displayed in the WebSphere Application Server administrative console and paste them to the TRIRIGA installation program fields to avoid typos or other errors. Do not install TRIRIGA into a WebSphere Application Server directory that contains a space. In addition, TRIRIGA cannot be used with cell, node, or server names that include an underscore or dash character.

- b. Specify the WebSphere Application Server administrator user name and password. The server must be running after this step to verify that the configuration was specified correctly and needed for the deployment.
- c. Optional: Define an alternative application context path that accesses the IBM TRIRIGA application. This path must begin with a slash (/).
- d. Specify the Java memory setting values in megabytes.
- e. Specify the server host name.
- 5. For the database type, select **Oracle**. Consult with your Oracle Database administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces, creating the schema, and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. When you create the database, you must load data using the installation program.
  - b. Specify the information for the data schema database server, such as the host name, port, and system identification (SID). For example, 1521 is a typical value for the Oracle Database server port, and orcl is a typical value for the Oracle Database server system identification.
  - **c**. Specify the data schema user name and password. For example, tridata is a typical value for both fields.
  - d. Specify the names of the data schema table spaces. Only letters and the underscore can be used in the table space name. For example, TRIDATA\_DATA is a typical value for data and TRIDATA\_INDX is a typical value for indexes.
  - e. Optional: Specify the data schema table space parameters, such as the file names and file sizes in megabytes. This screen is displayed if you chose to create the table spaces. The default file size is 2500 MB (or 2.5 GB), which is the minimum that is required. To determine the correct size of these files, conduct a careful analysis. If the autoextend option is enabled for table spaces within the database, the table spaces are automatically extended as needed. However, this extension might severely affect performance.
  - f. Optional: Specify the database administrator user name and password. This screen is displayed if you chose to create the table spaces and schema. This information is required to set up the database structures and schema owner. You are not prompted to specify the database administrator user if you chose to load the database from a .zip file as the only database action to perform.
  - g. Review the URL that the installer is using to test the data schema connection.
  - h. Review the results of the test. If the test fails, verify that Oracle Database is running. If you see an informative message that your database might not properly support multibyte characters and your implementation must support multibyte characters, then click **Cancel**. Adjust your database and restart the installer.
  - i. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click **Install**.

#### 7. Click Next.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. When the installation is complete, click **Done**.
- 9. Confirm that your license files are in the <code>tririga\_root</code>\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 10. Restart IBM TRIRIGA by locating the WebSphere Application Server directory with the appropriate method.
  - On Windows servers, start the WebSphere Application Server service IBM WebSphere Application Server V8.5 - NODENAME from Control Panel > Administrative Tools > Services.
  - On UNIX servers, run the stopServer and startServer commands and specify the server name, WEBSPHERE\_HOME/profiles/AppSrv01/bin/ stopServer.sh SERVER\_NAME and then WEBSPHERE\_HOME/profiles/AppSrv01/ bin/startServer.sh SERVER NAME.
  - Alternatively, you can start the application through the WebSphere
    Application Server admin console. Log into the WebSphere Application
    Server admin console, go to Applications > All Applications, select the
    IBM TRIRIGA application and click Stop and then Start.

#### What to do next

Verify that your installation is running properly.

## Installing IBM TRIRIGA Application Platform on WebSphere and Microsoft SQL Server

After your application server and database server are prepared, you can begin to install the IBM TRIRIGA Application Platform on IBM WebSphere Application Server and Microsoft SQL Server.

#### Before you begin

Verify that the Microsoft SQL Server and IBM WebSphere Application Server are running and that you have administrative authority on the servers.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - **c**. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select **New Database (data.zip required)** and then select the data file to install.
- 2. Select the data file to install and click Choose.

- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **IBM WebSphere Application Server** (**Standalone**). Specify the WebSphere Application Server information in the next set of screens.
  - a. Specify the information for the WebSphere Application Server configuration, such as the cell, node, server, profile, and home. Log on to the WebSphere Application Server and run the manageprofiles. [bat|sh] —listProfiles command to identify the cell, node, server, profile, and home values. WebSphere Application Server home is defined as C:\Program Files\IBM\WebSphere\AppServer, for example. Copy values displayed in the WebSphere Application Server administrative console and paste them to the TRIRIGA installation program fields to avoid typos or other errors. Do not install TRIRIGA into a WebSphere Application Server directory that contains a space. In addition, TRIRIGA cannot be used with cell, node, or server names that include an underscore or dash character.
  - b. Specify the WebSphere Application Server administrator user name and password. The server must be running after this step to verify that the configuration was specified correctly and needed for the deployment.
  - c. Optional: Define an alternative application context path that accesses the IBM TRIRIGA application. This path must begin with a slash (/).
  - d. Specify the Java memory setting values in megabytes.
  - e. Specify the server host name.
- 5. For the database type, select **Microsoft SQL Server**. Consult with your Microsoft SQL Server administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces, creating the schema, and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. When you create the database, you must load data using the installation program.
  - b. Specify the information for the database server connection, such as the port and name. For example, 1433 is a typical value for the Microsoft SQL Server port, and tridata is a typical value for the Microsoft SQL Server database name.
  - c. Specify the database user name and password. For example, tridata is a typical value for both fields. Verify that the database user that is being used for the new installation is uniquely associated to the database.
  - d. Choose a collation for the Microsoft SQL Server database.
  - e. Specify the database administrator user name and password. This information is required to set up the database structures and schema owner. You are not prompted to specify the database administrator user if you chose to load the database from a .zip file as the only database action to perform.
  - f. Review the URL that the installer is using to test the data schema connection.
  - g. Review the results of the test. If the test fails, verify that Microsoft SQL Server is running.
  - h. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.

- a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
- b. Review the pre-installation summary and click **Install**.

#### 7. Click Next.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. When the installation is complete, click **Done**.
- 9. Confirm that your license files are in the <code>tririga\_root</code>\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 10. Restart IBM TRIRIGA by locating the WebSphere Application Server directory with the appropriate method.
  - On Windows servers, start the WebSphere Application Server service IBM WebSphere Application Server V8.5 - NODENAME from Control Panel > Administrative Tools > Services.
  - On UNIX servers, run the stopServer and startServer commands and specify the server name, WEBSPHERE\_HOME/profiles/AppSrv01/bin/ stopServer.sh SERVER\_NAME and then WEBSPHERE\_HOME/profiles/AppSrv01/ bin/startServer.sh SERVER NAME.
  - Alternatively, you can start the application through the WebSphere
    Application Server admin console. Log into the WebSphere Application
    Server admin console, go to Applications > All Applications, select the
    IBM TRIRIGA application and click Stop and then Start.

#### What to do next

Verify that your installation is running properly.

## Installing TRIRIGA Application Platform on WebSphere and IBM DB2

After your application server and database server are prepared, you can begin to install the TRIRIGA Application Platform on IBM WebSphere Application Server and IBM DB2.

#### Before you begin

Verify that the IBM DB2 and IBM WebSphere Application Server are running and that you have administrative authority on the servers. Ensure the IBM DB2 database instance and the database have been configured for TRIRIGA.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - **c**. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.

- e. For the installation type, select New Database (data.zip required) and then select the data file to install.
- 2. Select the data file to install and click Choose.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **IBM WebSphere Application Server** (Standalone). Specify the WebSphere Application Server information in the next set of screens.
  - a. Specify the information for the WebSphere Application Server configuration, such as the cell, node, server, profile, and home. Log on to the WebSphere Application Server and run the manageprofiles. [bat | sh] **-listProfiles** command to identify the cell, node, server, profile, and home values. WebSphere Application Server home is defined as C:\Program Files\IBM\WebSphere\AppServer, for example. Copy values displayed in the WebSphere Application Server administrative console and paste them to the TRIRIGA installation program fields to avoid typos or other errors. Do not install TRIRIGA into a WebSphere Application Server directory that contains a space. In addition, TRIRIGA cannot be used with cell, node, or server names that include an underscore or dash character.
  - b. Specify the WebSphere Application Server administrator user name and password. The server must be running after this step to verify that the configuration was specified correctly and needed for the deployment.
  - c. Optional: Define an alternative application context path that accesses the IBM TRIRIGA application. This path must begin with a slash (/).
  - d. Specify the Java memory setting values in megabytes.
  - e. Specify the server host name.
- 5. For the database type, select **IBM DB2**. Consult with your IBM DB2 administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. For example, if your database administrator pre-created the table space, clear the first option. When you create the database, you must load data using the installation program.
  - b. Specify the information for the data schema database server, such as the host name, port, and database name. For example, 50006 is a typical value for the IBM DB2 server port, and tririga is a typical value for the IBM DB2 database name.
  - c. Specify the IBM TRIRIGA database user name and password. For example, tridata is a typical value for the database user name.
  - d. Specify the names of the data schema table spaces. Only letters and the underscore can be used in the table space name. For example, TRIDATA DATA is a typical value for data and TRIDATA INDX is a typical value for indexes.
  - e. Review the URL that the installer is using to test the data schema connection.
  - f. Review the results of the test. If the test fails, verify that IBM DB2 is running. If you see an informative message that your database might not properly support multibyte characters and your implementation must support multibyte characters, then click Cancel. Adjust your database and restart the installer. For the IBM TRIRIGA Application Platform to work correctly, the instance must be configured to use Oracle compatibility

- mode. To support multibyte characters, the codeset of the IBM DB2 instance must support UTF-8 and **string units** must be set to CODEUNITS32.
- g. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- **6**. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click Install.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. When the installation is complete, click **Done**.
- 9. Confirm that your license files are in the <a href="tririga\_root">tririga\_root</a>\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 10. Restart IBM TRIRIGA by locating the WebSphere Application Server directory with the appropriate method.
  - On Windows servers, start the WebSphere Application Server service IBM WebSphere Application Server V8.5 - NODENAME from Control Panel > Administrative Tools > Services.
  - On UNIX servers, run the **stopServer** and **startServer** commands and specify the server name, WEBSPHERE\_HOME/profiles/AppSrv01/bin/stopServer.sh SERVER\_NAME and then WEBSPHERE\_HOME/profiles/AppSrv01/bin/startServer.sh SERVER\_NAME.
  - Alternatively, you can start the application through the WebSphere
    Application Server admin console. Log into the WebSphere Application
    Server admin console, go to Applications > All Applications, select the
    IBM TRIRIGA application and click Stop and then Start.

#### What to do next

Verify that your installation is running properly.

#### Related concepts:

"Create and configure a DB2 database for TRIRIGA" on page 15 To configure TRIRIGA with DB2 version 10.5, you must create a database before you start the TRIRIGA Application Platform installation program. You can either create the database manually, or, you can use scripts that are provided with TRIRIGA.

# Installing IBM TRIRIGA Application Platform on Oracle WebLogic Server

TRIRIGA Application Platform can be installed on Oracle WebLogic Server and supported by a variety of database software. During the TRIRIGA Application Platform installation process, you can select the type of application server you want to use.

# Overview of IBM TRIRIGA Application Platform installation on WebLogic

Before you begin the IBM TRIRIGA Application Platform installation, Oracle WebLogic Server must be installed locally or on a server.

#### Oracle WebLogic Server installation programs

#### **IBM TRIRIGA Application Platform installation phases**

Use the generic Oracle WebLogic Server installation program to install the 64-bit version of Oracle WebLogic Server. The operating system specific versions of the Oracle WebLogic Server installation program are 32-bit only.

Installing the platform on the WebLogic Server involves several phases:

- Preparing the WebLogic Server settings.
- Starting the IBM TRIRIGA installation.
- Finishing the IBM TRIRIGA installation.

### **Preparing WebLogic**

When the Oracle WebLogic Server is running, you can prepare it for installation by clearing Oracle WebLogic Server cached files.

#### Before you begin

Verify that WebLogic Server is running and that you have administrative authority on the application server. IBM TRIRIGA is supported on 64-bit versions of WebLogic Server only.

For Linux systems, the bash shell must be installed on the system in order to configure WebLogic Server with IBM TRIRIGA.

#### About this task

Delete WebLogic Server caches by removing the Admin Server tmp folder and the JSP cache folder if they exist. The file paths to these folders vary as they are specific to your domain and server name. The following are examples of what the paths look like: \( \mathbb{WL\_INSTALL\_FOLDER/user\_projects/domains/my\_domain/servers/ \) AdminServer/tmp and \( \mathbb{WL\_INSTALL\_FOLDER/user\_projects/domains/my\_domain/ \) tmp jsp compile DefaultWebApp.

IBM TRIRIGA is deployed on a WebLogic Server Managed Server. Managed Servers are managed by a WebLogic Server Administrative Server. You must define a WebLogic Server domain, for example, tririgaManagedServer, that includes the WebLogic Server Administrative and Managed Server you want to use for the IBM TRIRIGA deployment. Refer to the Oracle WebLogic Server product documentation for information on how to use the Oracle Fusion Middleware Configuration Wizard to create a WebLogic Server Administrative Server, WebLogic Server Managed Server, and how to define a domain.

The IBM TRIRIGA Application Platform installation program sets the value of the WebLogic Server **enforce-valid-basic-auth-credentials** parameter to false during the installation process. If the security policy for your organization requires this value to be set to true, then IBM TRIRIGA CAD Integrator/Publisher users must be added to the WebLogic Server security repository. Refer to the Oracle WebLogic Server product documentation for more information.

Install the platform with the Oracle Database, IBM DB2, or Microsoft SQL Server.

# Installing IBM TRIRIGA Application Platform on WebLogic and Oracle Database

After your application server and database server are prepared, you can begin to install the IBM TRIRIGA Application Platform on Oracle WebLogic Server and Oracle Database.

#### Before you begin

Verify that the Oracle Database and Oracle WebLogic Server are running and that you have administrative authority on the servers.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - c. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select **New Database (data.zip required)** and then select the data file to install.
- 2. Select the data file to install and click **Choose**.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **Oracle WebLogic 12c (Standalone)**. Specify the WebLogic Server information in the next set of screens.
  - a. Select Oracle WebLogic 12c (Standalone).
  - b. Specify the paths to your WebLogic Server home and Domain Home directories..
  - **c**. Specify the appropriate information for your WebLogic Server host, including the admin server port. Enter the server password.
  - d. Specify the Java memory setting values in megabytes.
  - **e.** Optional: Define an alternative application context path to access the IBM TRIRIGA application. This path must begin with a slash (/).
  - f. Specify the path to the xercesImpl.jar file.
- 5. For the database type, select **Oracle**. Consult with your Oracle Database administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces, creating the schema, and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. When you create the database, you must load data using the installation program.
  - b. Specify the information for the data schema database server, such as the host name, port, and system identification (SID). For example, 1521 is a typical value for the Oracle Database server port, and orcl is a typical value for the Oracle Database server system identification.
  - c. Specify the data schema user name and password. For example, tridata is a typical value for both fields.

- d. Specify the names of the data schema table spaces. Only letters and the underscore can be used in the table space name. For example, TRIDATA\_DATA is a typical value for data and TRIDATA\_INDX is a typical value for indexes.
- e. Optional: Specify the data schema table space parameters, such as the file names and file sizes in megabytes. This screen is displayed if you chose to create the table spaces. The default file size is 2500 MB (or 2.5 GB), which is the minimum that is required. To determine the correct size of these files, conduct a careful analysis. If the autoextend option is enabled for table spaces within the database, the table spaces are automatically extended as needed. However, this extension might severely affect performance.
- f. Optional: Specify the database administrator user name and password. This screen is displayed if you chose to create the table spaces and schema. This information is required to set up the database structures and schema owner. You are not prompted to specify the database administrator user if you chose to load the database from a .zip file as the only database action to perform.
- g. Review the URL that the installer is using to test the data schema connection.
- h. Review the results of the test. If the test fails, verify that Oracle Database is running. If you see an informative message that your database might not properly support multibyte characters and your implementation must support multibyte characters, then click **Cancel**. Adjust your database and restart the installer.
- i. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click **Install**.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. Start the WebLogic Server when prompted.
- 9. When the installation is complete, click **Done**.
- 10. Confirm that your license files are in the <a href="tririga\_root">tririga\_root</a>\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 11. Start IBM TRIRIGA by starting the WebLogic Server Node Manager, Administration Server, and Managed Server.

If the installation failed, see the topic about validating the deployment on WebLogic Server and Oracle Database.

Verify that your installation is running properly.

# Validating the IBM TRIRIGA Application Platform deployment on WebLogic and Oracle Database:

If the IBM TRIRIGA Application Platform installation failed, it is still possible to run IBM TRIRIGA on Oracle WebLogic Server and Oracle Database by validating the data sources and deployment.

- 1. Verify the WebLogic Server configuration. Read the ant.log file in the root installation directory. If the last messages in the log discuss the WebLogic Server setup, then the setup must be completed manually.
- 2. Log in to the WebLogic Server administration console.
- 3. Verify that the IBM TRIRIGA Java Database Connectivity (JDBC) data sources are created. In the Domain Structure section, select **Services** > **Data Sources**.
- 4. In the main panel, verify that at least one data source with a Java Naming and Directory Interface (JNDI) name of jdbc/local/DataSource-TRIRIGA-data exists.
  - a. If the data source exists, continue to verify that the installation is correct.
  - b. If the data source does not exist, continue to create the data source.
- 5. In the main panel, click **New** and specify the following data source information:
  - a. For the name, specify DataSource-TRIRIGA-data.
  - b. For the JNDI name, specify jdbc/local/DataSource-TRIRIGA-data.
  - c. For the database type, select **Oracle**, and click **Next**.
  - d. For the database driver, select \*Oracle's Driver (Thin) for Instance connections; Versions:9.0.1 and later.
  - e. Click Next on each screen to move to the next screen.
- 6. For the database server, specify the database name, host name, database user name, and password.
- 7. Specify the following database information:
  - a. For the URL, specify jdbc:oracle:thin:@DatabaseServer:1521:orcl where DatabaseServer is the host name or IP of your database server, 1521 is the port number of the Oracle Database, and orcl is the system identification (SID) of the Oracle Database instance.
  - b. For the driver class name, specify oracle.jdbc.OracleDriver.
  - c. For the properties, do not change the default value that contains user=schemaname such as user=tridata.
  - d. For the password, specify and confirm the password for your TRIDATA schema.
  - e. For the test table name, do not change the default value.
  - f. For the database user name, specify the user name of your TRIDATA schema.
- 8. Click **Test Configuration**.

- 9. Select the check box for the server name of the IBM TRIRIGA deployment and click **Finish**.
- 10. Validate the IBM TRIRIGA data source. In the Domain Structure section, select Services > JDBC > Data Sources.
- 11. In the main panel, select DataSource-TRIRIGA-data.
- 12. Select the **Configuration** tab, and select the **General** tab. Verify that the JNDI name is jdbc/local/DataSource-TRIRIGA-data. The JNDI name is case-sensitive.
- 13. Select the **Connection Pool** tab. Verify that the URL, driver class name, and properties are correct. Change the maximum capacity to 100. You might be required to increase the maximum capacity as you add more users to the implementation. Click **Save**.
- 14. Select the **Targets** tab. Select the check box for the server that ties the data source to the server.
- 15. Validate the IBM TRIRIGA deployment. In the Domain Structure section, select **Deployments**. In the main panel, verify that the **ibm-tririga** application is deployed.
- 16. If the application is deployed, select **ibm-tririga** in the Deployments section.
- 17. If the application is not deployed:
  - a. Select Install.
  - b. For the path, select the IBM TRIRIGA installation directory, and select the ibm-tririga.war file. Click **Next** on each screen to move to the next screen.
  - c. Select Install this deployment as an application.
  - d. Click Finish.
- 18. Verify that data collection performance settings are configured.
  - a. In the Domain Structure, select **Services** > **Data Sources**. Select the Data Source named **DataPool**.
  - b. Select the Connection Pool tab, and verify that the following properties are included in the Properties section. If these properties are not found, add them and save the changes.

user=*username* DatabaseName=*databasename* 

- 19. Review the settings for the **ibm-tririga** application.
  - a. Optional: Restart the WebLogic Server to verify that everything is synchronized and in place for production.

#### What to do next

Verify that your installation is running properly.

# Installing IBM TRIRIGA Application Platform on WebLogic and Microsoft SQL Server

After your application server and database server are prepared, you can begin to install the IBM TRIRIGA Application Platform on Oracle WebLogic Server and Microsoft SQL Server.

#### Before you begin

Verify that the Microsoft SQL Server and Oracle WebLogic Server are running and that you have administrative authority on the servers.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - c. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select **New Database (data.zip required)** and then select the data file to install.
- 2. Select the data file to install and click Choose.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **Oracle WebLogic 12c (Standalone)**. Specify the WebLogic Server information in the next set of screens.
  - a. Select Oracle WebLogic 12c (Standalone).
  - b. Specify the paths to your WebLogic Server home and Domain Home directories..
  - **c.** Specify the appropriate information for your WebLogic Server host, including the admin server port. Enter the server password.
  - d. Specify the Java memory setting values in megabytes.
  - e. Optional: Define an alternative application context path to access the IBM TRIRIGA application. This path must begin with a slash (/).
  - f. Specify the path to the xercesImpl.jar file.
- 5. For the database type, select **Microsoft SQL Server**. Consult with your Microsoft SQL Server administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces, creating the schema, and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. When you create the database, you must load data using the installation program.
  - b. Specify the information for the database server connection, such as the port and name. For example, 1433 is a typical value for the Microsoft SQL Server port, and tridata is a typical value for the Microsoft SQL Server database name.
  - c. Specify the database user name and password. For example, tridata is a typical value for both fields. Verify that the database user that is being used for the new installation is uniquely associated to the database.
  - d. Choose a collation for the Microsoft SQL Server database.
  - e. Specify the database administrator user name and password. This information is required to set up the database structures and schema owner. You are not prompted to specify the database administrator user if you chose to load the database from a .zip file as the only database action to perform.
  - f. Review the URL that the installer is using to test the data schema connection.
  - g. Review the results of the test. If the test fails, verify that Microsoft SQL Server is running.

- h. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click Install.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. Start the WebLogic Server when prompted.
- 9. When the installation is complete, click **Done**.
- 10. Confirm that your license files are in the tririga\_root\config\licenses directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 11. Start IBM TRIRIGA by starting the WebLogic Server Node Manager, Administration Server, and Managed Server.

#### What to do next

If the installation failed, see the topic about validating the deployment on WebLogic Server and Microsoft SQL Server.

Verify that your installation is running properly.

# Validating the IBM TRIRIGA deployment on WebLogic and Microsoft SQL Server:

If the IBM TRIRIGA Application Platform installation failed, it is still possible to run IBM TRIRIGA on Oracle WebLogic Server and Microsoft SQL Server by validating the data sources and deployment.

- 1. Verify the WebLogic Server configuration. Read the ant.log file in the root installation directory. If the last messages in the log discuss the WebLogic Server setup, then the setup must be completed manually.
- 2. Log in to the WebLogic Server administration console.
- 3. Verify that the IBM TRIRIGA Java Database Connectivity (JDBC) data sources are created. In the Domain Structure section, select **Services** > **Data Sources**.
- 4. In the main panel, verify that at least one data source with a Java Naming and Directory Interface (JNDI) name of jdbc/local/DataSource-TRIRIGA-data exists.
  - a. If the data source exists, continue to verify that the installation is correct.
  - b. If the data source does not exist, continue to create the data source.
- 5. In the main panel, click **New** and specify the following data source information:

- a. For the name, specify DataSource-TRIRIGA-data.
- b. For the JNDI name, specify jdbc/local/DataSource-TRIRIGA-data.
- c. For the database type, select MS SQL Server, and click Next.
- d. For the database driver, select **Other**.
- e. Click Next on each screen to move to the next screen.
- 6. For the database server, specify the database name, host name, database user name, and password.
- 7. Specify the following database information:
  - a. For the URL, specify jdbc:jtds:sqlserver://hostname:db.port/ db.name;tds=8.0;SendStringParametersAsUnicode=mbcs;prepareSQL=2 where hostname is the host name or IP of your database server, db.port is the port number of the Microsoft SQL Server database (such as 1433), db.name is the database name, and mbcs is true for multibyte support.
  - b. For the driver class name, specify net.sourceforge.jtds.jdbc.Driver.
  - c. For the properties, specify user=username such as user=tridata.
  - d. For the password, specify and confirm the password for your TRIDATA schema.
  - e. For the test table name, specify SQL SELECT 1.
  - f. For the database user name, specify the user name of your TRIDATA schema.
- 8. Click **Test Configuration**.
- 9. Select the check box for the server name of the IBM TRIRIGA deployment and click **Finish**.
- 10. Validate the IBM TRIRIGA data source. In the Domain Structure section, select **Services** > **JDBC** > **Data Sources**.
- 11. In the main panel, select **DataSource-TRIRIGA-data**.
- 12. Select the **Configuration** tab, and select the **General** tab. Verify that the JNDI name is jdbc/local/DataSource-TRIRIGA-data. The JNDI name is case-sensitive.
- 13. Select the **Connection Pool** tab. Verify that the URL, driver class name, and properties are correct. Change the maximum capacity to 100. You might be required to increase the maximum capacity as you add more users to the implementation. Click **Save**.
- 14. Select the **Targets** tab. Select the check box for the server that ties the data source to the server.
- 15. Validate the IBM TRIRIGA deployment. In the Domain Structure section, select **Deployments**. In the main panel, verify that the **ibm-tririga** application is deployed.
- **16**. Verify that data collection performance settings are configured.
  - a. In the Domain Structure, select **Services** > **Data Sources**. Select the Data Source named **DataPool**.
  - b. Select the Connection Pool tab, and verify that the following properties are included in the Properties section. If these properties are not found, add them and save the changes.
    - user=*username* DatabaseName=*databasename*
- 17. If the application is deployed, select **ibm-tririga** in the Deployments section.
- **18**. If the application is not deployed:
  - a. Select Install.

- b. For the path, select the IBM TRIRIGA installation directory, and select the ibm-tririga.war file. Click **Next** on each screen to move to the next screen.
- c. Select Install this deployment as an application.
- d. Click Finish.
- 19. Review the settings for the ibm-tririga application.
  - a. Optional: Restart the WebLogic Server to verify that everything is synchronized and in place for production.

Verify that your installation is running properly.

# Installing IBM TRIRIGA Application Platform on WebLogic and IBM DB2

After your application server and database server are prepared, you can begin to install the IBM TRIRIGA Application Platform on Oracle WebLogic Server and IBM DB2.

#### Before you begin

Verify that the IBM DB2 and Oracle WebLogic Server are running and that you have administrative authority on the servers.

- 1. Run the installer file. Follow the installation instructions.
  - a. Accept the license.
  - b. Check for the latest available fix pack and apply it.
  - c. Choose the Java Virtual Machine to use with the installation program. The 64-bit version of Java 8 is required.
  - d. Select the installation folder.
  - e. For the installation type, select **New Database (data.zip required)** and then select the data file to install.
- 2. Select the data file to install and click Choose.
- 3. Optional: If license files for this product are stored on this system, specify the full path to their location.
- 4. For the application server, select **Oracle WebLogic 12c (Standalone)**. Specify the WebLogic Server information in the next set of screens.
  - a. Select Oracle WebLogic 12c (Standalone).
  - b. Specify the paths to your WebLogic Server home and Domain Home directories.
  - **c**. Specify the appropriate information for your WebLogic Server host, including the admin server port. Enter the server password.
  - d. Specify the Java memory setting values in megabytes.
  - e. Optional: Define an alternative application context path to access the IBM TRIRIGA application. This path must begin with a slash (/).
  - f. Specify the path to the xercesImpl.jar file.
- 5. For the database type, select **IBM DB2**. Consult with your IBM DB2 administrator and specify the database information in the next set of screens.
  - a. Select the database actions to be initiated, such as creating table spaces and loading the database from a .zip file. Some of these tasks can be completed by the database administrator beforehand. For example, if your

- database administrator pre-created the table space, clear the first option. When you create the database, you must load data using the installation program.
- b. Specify the information for the data schema database server, such as the host name, port, and database name. For example, 50006 is a typical value for the IBM DB2 server port, and tririga is a typical value for the IBM DB2 database name.
- **c**. Specify the IBM TRIRIGA database user name and password. For example, tridata is a typical value for the database user name.
- d. Specify the names of the data schema table spaces. Only letters and the underscore can be used in the table space name. For example, TRIDATA\_DATA is a typical value for data and TRIDATA\_INDX is a typical value for indexes.
- e. Review the URL that the installer is using to test the data schema connection.
- f. Review the results of the test. If the test fails, verify that IBM DB2 is running. If you see an informative message that your database might not properly support multibyte characters and your implementation must support multibyte characters, then click Cancel. Adjust your database and restart the installer. For the IBM TRIRIGA Application Platform to work correctly, the instance must be configured to use Oracle compatibility mode. To support multibyte characters, the codeset of the IBM DB2 instance must support UTF-8 and string units must be set to CODEUNITS32.
- g. Specify the sizes for the database pools. These settings determine the number of connections that the application server starts when it initializes and the number that it can grow to under load.
- 6. Complete and review the installation information in the final set of screens.
  - a. Specify the names of the Simple Mail Transfer Protocol (SMTP) mail server and front end server.
  - b. Review the pre-installation summary and click Install.

- a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 8. Start the WebLogic Server when prompted.
- 9. When the installation is complete, click **Done**.
- 10. Confirm that your license files are in the <code>tririga\_root\config\licenses</code> directory. If they are not, you must copy them to this directory. All application servers that access a database must have the same set of licenses. The only exception is the license file for the IBM TRIRIGA Connector for Business Applications. This product is licensed for a limited number of servers and the license file must be placed on that number of servers to stay in compliance. For more information, see the topic about license files.
- 11. Start IBM TRIRIGA by starting the WebLogic Server Node Manager, Administration Server, and Managed Server.

#### What to do next

If the installation failed, see the topic about validating the deployment on WebLogic Server and IBM DB2.

Verify that your installation is running properly.

#### Related concepts:

"Create and configure a DB2 database for TRIRIGA" on page 15 To configure TRIRIGA with DB2 version 10.5, you must create a database before you start the TRIRIGA Application Platform installation program. You can either create the database manually, or, you can use scripts that are provided with TRIRIGA.

# Validating the IBM TRIRIGA Application Platform deployment on WebLogic and IBM DB2:

If the IBM TRIRIGA Application Platform installation failed, it is still possible to run IBM TRIRIGA on Oracle WebLogic Server and IBM DB2 by validating the data sources and deployment.

- 1. Verify the WebLogic Server configuration. Read the ant.log file in the root installation directory. If the last messages in the log discuss the WebLogic Server setup, then the setup must be completed manually.
- 2. Log in to the WebLogic Server administration console.
- 3. Verify that the IBM TRIRIGA Java Database Connectivity (JDBC) data sources are created. In the Domain Structure section, select **Services** > **Data Sources**.
- 4. In the main panel, verify that at least one data source with a Java Naming and Directory Interface (JNDI) name of jdbc/local/DataSource-TRIRIGA-data exists.
  - a. If the data source exists, continue to verify that the installation is correct.
  - b. If the data source does not exist, continue to create the data source.
- 5. In the main panel, click **New** and specify the following data source information:
  - a. For the name, specify DataSource-TRIRIGA-data.
  - b. For the JNDI name, specify jdbc/local/DataSource-TRIRIGA-data.
  - c. For the database type, select **DB2**, and click **Next**.
  - d. For the database driver, select IBM's DB2 Driver (Type 4) for JDBC and SQLJ; Versions:8.X and later.
  - e. Click Next on each screen to move to the next screen.
- 6. For the database server, specify the database name, host name, database user name, and password.
- 7. Specify the following database information:
  - a. For the URL, specify jdbc:db2:DatabaseServer:50000/DatabaseName where DatabaseServer is the host name or IP of your database server, 50000 is the port number of the IBM DB2 instance, and DatabaseName is the name of the database.
  - b. For the driver class name, specify com.ibm.db2.jcc.DB2Driver.
  - **c**. For the properties, do not change the default value that contains user=*databaseusername* such as user=tridata.
  - d. For the password, specify and confirm the password for your TRIDATA schema.
  - e. For the test table name, do not change the default value.
  - For the database user name, specify the user name of your TRIDATA schema.

- 8. Click Test Configuration.
- 9. Select the check box for the server name of the IBM TRIRIGA deployment and click **Finish**.
- 10. Validate the IBM TRIRIGA data source. In the Domain Structure section, select **Services** > **JDBC** > **Data Sources**.
- 11. In the main panel, select **DataSource-TRIRIGA-data**.
- 12. Select the **Configuration** tab, and select the **General** tab. Verify that the JNDI name is jdbc/local/DataSource-TRIRIGA-data. The JNDI name is case-sensitive.
- 13. Select the **Connection Pool** tab. Verify that the URL, driver class name, and properties are correct. Change the maximum capacity to 100. You might be required to increase the maximum capacity as you add more users to the implementation. Click **Save**.
- 14. Select the **Targets** tab. Select the check box for the server that ties the data source to the server.
- 15. Validate the IBM TRIRIGA deployment. In the Domain Structure section, select **Deployments**. In the main panel, verify that the **ibm-tririga** application is deployed.
- 16. Verify that data collection performance settings are configured.
  - a. In the Domain Structure, select **Services** > **Data Sources**. Select the Data Source named **DataPool**.
  - b. Select the Connection Pool tab, and verify that the following properties are included in the Properties section. If these properties are not found, add them and save the changes.

```
user=username
jdbcCollection=NULLIDR1
DatabaseName=databasename
```

- 17. If the application is deployed, select **ibm-tririga** in the Deployments section.
- **18**. If the application is not deployed:
  - a. Select Install.
  - b. For the path, select the IBM TRIRIGA installation directory, and select the ibm-tririga.war file. Click **Next** on each screen to move to the next screen.
  - c. Select Install this deployment as an application.
  - d. Click Finish.
- 19. Review the settings for the **ibm-tririga** application.
  - a. Optional: Restart the WebLogic Server to verify that everything is synchronized and in place for production.

Verify that your installation is running properly.

# Installing IBM TRIRIGA Application Platform with Oracle Database export files

If you have an Oracle Database export file to import into the IBM TRIRIGA Application Platform installation, you can run an Oracle Database export installation.

### Overview of Oracle Database export installation

If you have an Oracle Database export file to import into the IBM TRIRIGA Application Platform installation, you can run an Oracle Database export

installation. You can run this type of installation to move an operational database to a test or staging environment, or restore a database after a failure.

#### Installation phases

Before you begin the IBM TRIRIGA Application Platform installation, the application server software must be installed locally or on a server. Installing the platform with an Oracle Database export file involves several phases:

- Running the IBM TRIRIGA installation as a new installation to set up the schema (or user) and the table spaces (or database).
- Importing the Oracle Database .dmp export file.
- Running the IBM TRIRIGA installation as an upgrade installation to load the database.

# Installing IBM TRIRIGA Application Platform on WebLogic or WebSphere

After your application server and database server are prepared, you can begin to install the IBM TRIRIGA Application Platform with your Oracle Database export file

#### Before you begin

Verify that the Oracle Database is running and that you have administrative authority on the database server.

#### **Procedure**

- 1. Run the installer file. Follow the installation instructions.
  - a. For the installation type, select New Database (data.zip required).
  - b. For the database type, select **Oracle**.
- 2. When you reach the database installation options, select the database action to create the schema. Clear all other options.
  - a. Optional: If the table spaces do not exist, select the database action to create the table spaces.
- 3. When you reach the pre-installation summary, click Install.
- 4. Click Next.
  - a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility. In Windows, you can run the WinTail utility. In UNIX, you can run the tail -f ant.log command.
- 5. When the installation is complete, click **Done**.
- 6. Import the Oracle Database .dmp export file.
  - a. Locate the export file and run the import command. For example:

imp system/manager fromuser=tridata touser=tridata
file=exp tridata.dmp log=imp tridata.log

- b. When the import is complete, note any warnings or errors that occurred.
- 7. Review the ant.log file for errors.
  - a. If an error is found, consult your implementation team on how to proceed.
  - b. If no errors are found, delete the ant.log file.
- 8. Run the installer file. Follow the installation instructions.
  - a. For the installation type, select **Existing Database**.
  - b. For the database type, select **Oracle**.

- 9. When you reach the pre-installation summary, click **Install**.
- 10. Click Next.
  - a. Optional: If you want to monitor the progress in the directory where IBM TRIRIGA is installed, you can open the ant.log file in a log monitoring utility.
- 11. When the installation is complete, click **Done**.
- 12. Review the ant.log file for errors.
  - a. If an error is found, consult your implementation team on how to proceed.
- 13. Verify that your license files are in the *tririga\_root*\config\licenses directory.
- 14. Optional: If you made customizations that were saved in the userfiles directory, copy those files into the upgrade installation.
- 15. Start IBM TRIRIGA by locating the application server directory with the appropriate method.

Verify that your installation is running properly.

### Verification checklist

After the IBM TRIRIGA Application Platform installation is complete, verify that your installation is running properly. This verification checklist is not intended to replace your company testing and validation procedures.

Item	Description		
Inspecting the installation log	Read the ant.log file. This file contains information about that steps that were taken during the installation. The file is written to the IBM TRIRIGA root installation directory. For example, on Windows, C:\Tririga\ant.log is the typical location.		
	A line toward the end of the file indicates whether the installation succeeded or failed, such as the following examples:		
	The installation succeeded:		
	BUILD SUCCESSFUL Total time: 25 minutes 51 seconds		
	The installation failed:		
	BUILD FAILED C:\Tririga\build.xml:2586: The following error occurred while executing this line: C:\Tririga\build.xml:2141: Java returned: -1		
	Total time: 8 minutes 44 seconds		
Starting the application	Start IBM TRIRIGA by locating the application server directory with the appropriate method.		

Item	Description
Accessing the application	Verify your access to the IBM TRIRIGA application as the system user as follows:
	• Specify the URL address in your browser address field. The URL looks something like http://[hostname:port][/context_path], where [hostname:port] and [/context_path] are the specific values for your
	environment. If you see the error message "Unable to launch the application", then you must set the <b>FRONT_END_SERVER</b> property.
	Sign in with your user name and password. The default user name is "system" and the default password is "admin".
Accessing the administrator console	Verify your access to the IBM TRIRIGA administrator console as follows.
	• Specify the URL address in your browser address field. The URL looks something like http://[hostname:port][/context_path]/html/en/default/admin, where [hostname:port] and [/context_path] are the specific values for your environment.
	• Sign in with your user name and password. The default user name is "system" and the default password is "admin".
	In the Agent Manager, start the following agents in the process server: Platform Maintenance Scheduler Agent, Extended Formula Agent, Formula Recalc Agent, Scheduler Agent, Workflow (WF) Agent, and Workflow (WF) Notification Agent.
	Sign out of the administrator console.
Creating users and records	As the system user, create and verify an IBM TRIRIGA employee who is not an administrator as follows:
	Assign the user to several user groups, but not all of them.
	Assign the user with several user licenses, but not all of them.
	Sign in as the user that you created.
	• Verify that the user can access everything that the employee is meant to access, according to the assigned groups and licenses.
	<ul> <li>Verify that the user can create and revise records, such as people records and location records.</li> </ul>
	<ul> <li>Verify that the association tree loads in the Associations tab of an opened record.</li> </ul>
Using the builder tools	As the system user, open and verify the builder tools under <b>Tools &gt; Builder Tools</b> as follows:
	In the workflow builder, verify that workflows load completely by opening and revising existing workflows.
	In the data modeler, verify that the state transitions load completely.
	<ul> <li>In the data modeler, verify that the simple mail transfer protocol (SMTP) email notification works by publishing a test business object.</li> </ul>

Item	Description		
Using the Document Manager	As either the system user or a user with rights, open and verify the Document Manager under Tools > Document Manager as follows:		
	• Verify that the user can upload new documents, such as .txt, .html, and .jpg files.		
	Verify that the user can upload new documents with the multifile applet.		
	<ul> <li>Verify that the user can view documents by clicking the icon in the V column.</li> </ul>		
	Verify that the user can check in and check out documents.		
	• If Brava is installed, verify that the user can upload computer-aided design (CAD) documents in .dxf format and view the CAD documents by clicking the icon in the V column.		
Editing project tasks	As either the system user or a user with rights, verify the functions as follows:		
	Create or open a new capital project.		
	• In the <b>Schedule</b> tab, add or open a task in the Project Tasks section.		
	• In the task, edit the planned start date, planned end date, or planned working hours.		
	• Verify that when one field is edited, the other two fields are adjusted automatically.		
Syncing CAD drawings	If IBM TRIRIGA CAD Integrator/Publisher is being used, verify your access to IBM TRIRIGA as follows:		
	Start TRIRIGA CAD Integrator/Publisher.		
	• Sign in as a user with a TRIRIGA CAD Integrator/Publisher license.		
	• Verify that the user can sync a CAD drawing with TRIRIGA CAD Integrator/Publisher.		
Inspecting the server log	Verify that the server.log file exists for each application server and process server. This file is written to the log directory of the IBM TRIRIGA installation. For example, on Windows, C:\Tririga\log\server.log is the typical location.		
	In addition:		
	• Verify that the application server is writing to its server.log file. Inspect the file for any major exceptions on first startup.		
	• Verify that the process server is writing to its server.log file. One day after the installation and on a regular basis, verify that the process server completed the cleanup process successfully.		

## **Configuring the platform**

Although the IBM TRIRIGA Application Platform installation process applies most of the required configurations, further configuration might be necessary for your particular implementation. You can avoid issues by determining what the key configurations are and where changes can be made to optimize your environment.

### **Properties files**

Certain IBM TRIRIGA properties must be set when they apply to your particular implementation. The properties files are in the config directory of the IBM TRIRIGA Application Platform installation. For example, on Windows, C:\Tririga\config is the typical location.

The properties files follow the concept of "name-value pairs" where a variable name is followed by an equal sign (=) and the defined value. Lines in the properties files that begin with a number sign (#) are comments and not read by the implementation. Name-value pairs are case-sensitive.

The variables and settings in the properties files might change from one version of IBM TRIRIGA to the next. Before you upgrade from a prior version of the IBM TRIRIGA software, save your old properties files. After you complete your upgrade installation, carefully review each newly installed properties file and adjust any values that apply to your implementation.

For information about the TRIRIGACRYSTAL.properties file, see the *IBM TRIRIGA Application Platform 3 Connector for SAP BusinessObjects User Guide*.

### **TRIRIGAWEB.**properties

To adjust the IBM TRIRIGA web application properties, open the TRIRIGAWEB.properties file. The application server must be restarted for changes in the TRIRIGAWEB.properties file to take effect.

#### File system settings

Property	Values	Description
FileSystemRoot	[Valid path]	The path to the userfiles directory.
		For example, C:/Tririga/userfiles.
FileSystemBrowseRoot	[Valid path]	The path to the userfiles directory.
		For example, C:/Tririga/userfiles.
BatchInputLoc	[Valid path]	The path to the directory where the batch upload data files are stored.
		For example, C:/Tririga/userfiles/input.
BatchProcessLoc	[Valid path]	The path to the directory where the batch upload data files are processed.
		For example, C:/Tririga/userfiles/processing.
BatchOutputLoc	[Valid path]	The path to the directory where the batch upload data process writes to the output log.
		For example, C:/Tririga/userfiles/output.
BatchErrorLoc	[Valid path]	The path to the directory where the batch upload data process writes to the error log.
		For example, C:/Tririga/userfiles/error.
BatchLogLoc	[Valid path]	The path to the directory where the batch upload data process writes to the running log.
		For example, C:/Tririga/userfiles/log.

Property	Values	Description
ServerRoot	[Valid path]	The path to the parent directory of the userfiles directory.  For example, C:/Tririga.

### **External server settings**

Property	Values	Description
mail.smtp.host	[Host name or IP address]	The simple mail transfer protocol (SMTP) mail server for delivering outgoing notifications and messages to external mail systems. This property is set to a host name or IP address. In most cases, the mail server must be listening on port 25.  The SMTP server must be configured to accept outgoing emails from the IP address of the IBM TRIRIGA server without authentication.  For example, LAPTOP234 and 10.11.12.13.
mail.smtp.email.domain	[String]	The SMTP mail server domain name for delivering outgoing notifications and messages. In most cases, the mail server must be listening on port 25. The platform tries to use this property value first, and if this property value is not set, the platform uses the value in mail.smtp.host.
		For example, mail.company.com.
mail.imaps.ssl.key	[String]	For the Incoming Mail Agent to connect to and process IMAPS requests where the SSL certificate is self signed, use this property to point to a keystore file on the local server that has been configured to accept and trust the IMAPS Server's SSL Key. This is the path on the server's file system to where the Secure Sockets Layer (SSL) keystore is loaded for the SSL connection. If no value is specified, but the Internet Message Access Protocol - Secure (IMAPS) is used for the Incoming Mail Agent, then the application server must set the keystore.
mail.imaps.ssl.port	[Number]	The default port setting for IMAPS.
		For example, 993.

You can add JavaMail API properties (mail.smtp.\*) to the TRIRIGAWEB.properties file that customize the behavior of the IBM TRIRIGA Application Platform mail framework. If you do not add these properties, default values and specifications are used.

### **Brava server settings**

Property	Values	Description
BRAVA_SERVER_URL	[URL]	The Brava Server URL. For example, http\://9.72.78.55\:8080
BRAVA_EXCLUDE_LIST	[Valid file extensions]	A list of file extensions to identify the files to be ignored by Brava. If no value is specified, then all file extensions are passed to Brava. Separate the file extensions in the list with commas. Do not include the dot (".") when you specify an extension.  For example, html,htm,svg,rpt,zip,exe,doc,xls,ppt,pdf,txt,xml
FRONT_END_SERVER	[Host name]	The URL used to access IBM TRIRIGA. It consists of a protocol, a host, [REQUIRED] and port (optional). The HTTP protocol is used by default.

## Agent settings

Property	Values	Description
AGENTS_NOT_ALLOWED	[String]	A comma-delimited list of agents that are not allowed to run on this server.
		Manage agent settings for this server and all other IBM TRIRIGA servers on the Agent Manager page of the administrator console. For more information, see the IBM TRIRIGA Application Platform 3 Administrator Console User Guide.
		A blank value allows any agent to be started on this server but does not start any agent automatically.
INSTANCE_ID	[Number]	Overrides the default computer ID.
		The INSTANCE properties override the default system ID and system name. If you leave these optional properties blank, a hostname lookup action is used to name the instance and calculate the ID.
		When two or more IBM TRIRIGA servers are running on the same physical computer, the INSTANCE_ID property must be unique for independent agent management. The INSTANCE_ID property must be set to a numeric value less than 10000.
		Leave this value blank if you are running a single instance per physical computer.

Property	Values	Description
INSTANCE_NAME	[String]	Overrides the default computer name.
		The INSTANCE properties override the default system ID and system name. If you leave these optional properties blank, a hostname lookup action is used to name the instance and calculate the ID.
		When two or more IBM TRIRIGA servers are running on the same physical computer, the INSTANCE_NAME property must be unique for independent agent management. When a value is present, the value of the INSTANCE_NAME property can be any alphanumeric value.
		Leave this value blank if you are running a single instance per physical computer.
ReportQueueAgentLoad	[Number]	The number of threads in proportion to the number of connections.
		For example, 100.0.
ReportQueueAgentMax	[Number]	The maximum number of threads.
Threads		If there is no upper limit, set to 0.
DataImportAgentMax Threads	[Number]	The number of threads in proportion to the number of connections.
		For example, 100.0.
DataImportAgentMax Threads	[Number]	The maximum number of threads.  If there is no upper limit, set to 0.
SchedulerAgentLoad	[Number]	The number of threads in proportion to the number of connections.
		For example, 100.0.
SchedulerAgentMax Threads	[Number]	The maximum number of threads.
inreads		If there is no upper limit, set to 0.
WFAgentLoad	[Number]	The number of threads in proportion to the number of connections.
		For example, 100.0.
WFAgentMaxThreads	[Number]	The maximum number of threads.
		If there is no upper limit, set to 0.
CadIntegratorLoad	[Number]	The maximum load.
		For example, 100.0.
CadIntegratorMaxThreads	[Number]	The maximum number of threads.
		For example, 4.
WF_AGENT_MAX_ACTIVE_PER	[Number]	The thread limit per user on active workflows.
_USER		Set this property to a low number to prevent one user from reaching the environment maximum.

Property	Values	Description
WF_NOTIFICATION_EMAIL _ID	[Valid email address]	The sent-from email address on outgoing workflow notifications.
		For example, wf.notifications@us.ibm.com
WF_NOTIFICATION_EMAIL _ID_FROM_DISPLAY _LABEL	[String]	Assign a title to outgoing emails sent from the address defined for WF_NOTIFICATION_EMAIL_ID.  For example, Workflow notifications <wf.notifications@us.ibm.com></wf.notifications@us.ibm.com>
NOTIFICATION_HTML _TAG_WHITELIST	[String]	Specifies the HTML tags that are allowed in outgoing email and can be used to allow images to be placed in outgoing mail.  To add to the comma delimited list, add the new HTML tag without spaces. When left blank, the default list will be used.  The default list contains: html,head,title,body, h1,h2,h3,h4,h5,h6,p,br,hr,pre,em,strong,code, b,i,a,ul,li,ol,dl,dd,dt,table,tr,td,thead,t body,th,input,form,select,option,textarea, blockquote,div,span,label,style

Property	Values	Description
WF_INSTANCE_SAVE F	PER _WORK FLOW _ALWAYS, ALWAYS, ERRORS _ONLY	Configures when workflow instances are saved. The property includes the following values:  • PER_WORKFLOW_ALWAYS: Save the instance if the workflow is configured to save.  • ALWAYS: Always save instances.  • ERRORS_ONLY: Save instances only when an error occurs (default).
		Instances that are required by the platform are saved as necessary regardless of this setting. Suspended workflows and workflows with errors are always saved.
		Changing this property within the TRIRIGAWEB.properties file requires restarting the server for the change to take effect.
		Workflow Agent Manager. You can change the setting from the administrator console without restarting the server. The Workflow Agent Manager contains a Workflow Instance Recording field and a Save action. The field contains the following options:
		• Never: Corresponds to the NEVER value.
		• <b>As configured in the workflow</b> : Corresponds to the PER_WORKFLOW_ALWAYS value.
		• Always: Corresponds to the ALWAYS value.
	Do not use the ALWAYS value in production environments. Do not use the ALWAYS value for an extended period of time. It will cause performance issues and excessive space consumption. It is better to use PER_WORKFLOW_ALWAYS in a development environment to isolate issues without saving instances of other unrelated application processes. Do not leave WF Instance set to ALWAYS for more than a few hours as you troubleshoot an issue Serious performance, memory, and database space problems will happen if you keep this setting.	
		There is also an option to restore from the TRIRIGAWEB.properties file.
		The setting takes effect as soon as you click <b>Save</b> . This setting affects the specific server on which the administrator console is being accessed; it does not apply across servers. This setting stays in effect until it is changed or until the server is restarted. Restarting the server reverts the setting to the value in the TRIRIGAWEB.properties file.

Property	Values	Description
USE_WF_BINARY_LOAD	N, Y	If set to Y, the platform uses the binary load process. The Workflow Templates are loaded with their stored binary version, if they cannot be found in the Workflow Template cache.  If set to N or no value, the platform skips the binary load process.  The default value is Y.
EDONT END CEDVED	[Host name	The main URL that the user enters to access the
FRONT_END_SERVER	[Host name or IP address]	IBM TRIRIGA application. It consists of a protocol (optional), host (required), and port (optional). If no protocol is specified, then "http://" is used by default.  For example:  tririga.company.com  tri-dev.company.com:8001  https://tri-secure.company.com  This property must be configured properly for
		Business Intelligence and Reporting Tools (BIRT) reports in IBM TRIRIGA to work correctly.  If your users are seeing an application error "Unable to launch the application", you must set this property. If you are not using Apache HTTP Server, enter the application server IP with the port number. For example, if your application server is running Oracle WebLogic Server on SERVER123, this property must be set to SERVER123:8001.
EXTERNAL_FRONT _END_SERVER=	[Host name or IP address]	The main URL an external user would click in an e-mail notification to access the IBM TRIRIGA system. It consists of a protocol, host, and, optionally, a port value. Do not add the context-path.  IBM TRIRIGA supports split horizon DNS, so internal and external users can access IBM TRIRIGA using the same URL. The DNS server delivers an internal IP address for internal personnel, and an external IP address for external personnel.
CLEAN_HOUR	[Whole number from 0 to 23]	The hour at which the Cleanup Agent starts, in 24-hour time.  The default value is 2.
CLEAN_TIMEOUT	[Whole number]	The number of minutes the Platform Maintenance Agent is allowed to run. The default value is 120.
DC_HISTORY_RETENTION _DAYS	[Number]	The DataConnect Agent deletes completed or obsolete DataConnect Jobs that are older than this number of days.  The default value is 5.

Property	Values	Description
WF_HISTORY_RETENTION _DAYS	[Number]	The Cleanup Agent deletes workflows that are not waiting on a user or on approval tasks that are older than this number of days.
		The default value is 10.
CLEANUP_AGENT_SCHEDULER _TASKS	N, Y	If set to Y, the platform runs the Scheduler Cleanup tasks.
		The default value is Y.
CLEANUP_AGENT_SCHEDULED _EVENT_COMPLETE_DAYS	[Number]	The platform moves scheduled events that were not completed in this many days to a completed state.
		The default value is 7 (1 week).
CLEANUP_TIMEOUT	[Number]	How long the cleanup agent can run, measured in minutes.
WF_AGENT_WAITTIME	[Number]	The number of milliseconds that the Workflow Agent waits before it checks for more free threads. This property is not the same as workflow sleep time.  The minimum value is 100.
WF_FUTURE_AGENT _SLEEPTIME	[Number]	The number of seconds that the Workflow Future Agent waits before it checks whether more items must be processed.  The default value is 5.
REPORTDATA_AGENT _SLEEPTIME	[Number]	The number of minutes that the Report Data Index Agent waits before it checks whether more items must be processed.  The default value is 5.
REPORTDATA_AGENT _RECORD_COUNT	[Number]	The number of records in a report before the Report Data Index Agent reindexes the report.  The default value is 500.
DATACONNECT_SLEEP_TIME	[Number]	The number of minutes that the DataConnect Agent waits before it checks whether more items must be processed.  Use a negative integer to indicate a value measured in seconds. For example, to check every ten seconds, use the value -10. Ten seconds is the shortest interval supported.
		The default value is 10.

Property	Values	Description
SHOW_ZEROS_IN_NUMBER _FIELDS	N, Y	Numeric fields can be configurable to display zero or empty when it is null
		When set to N, all null currency and field numbers are displayed empty. A number field renders empty in a form and in a query with no editable fields when the value in the database is null.
		When set to Y the fields are filled with 0 or .00. A number field renders zero in a form and in a query with no editable fields when the value in the database is null.
		The default value is Y.
TDI_AGENT_SLEEPTIME	[Number]	The number of minutes that the agent waits before it checks to ensure the Tivoli Directory Integrator server is running. If the server is not running, the agent restarts it.
		The default value is 2.
TDI_INSTALL_DIR	[Number]	The directory where you installed TDI. For example, TDI_INSTALL_DIR=C:/Program Files/IBM/TDI/V7.1.1
TDI_HTTP_SERVER_PORT	[Number]	The port used to send requests to the Tivoli Directory Integrator server. IBM TRIRIGA uses this port to send ETL transforms to the Tivoli Directory Integrator server to process.
		The default value is 8088.
TDI_SERVER_TIMEOUT	[Number]	The number of seconds to wait for a successful start or stop command of the Tivoli Directory Integrator server before a failure is reported.
		The default value is 60.
TDI_SERVER_PORT	[Number]	Port used by the Tivoli Directory Integrator server.

### System settings

Property	Values	Description
BaseCurrency	[Valid currency]	The base currency for currency conversions.  An administrator must set this value at the time of installation. Evaluate your use of currencies during implementation and add or remove currencies that are necessary to your business before you add records. Failure to do so before you create records can cause conversion issues or data loss on those records. Changing the currency after the transaction records have been created is not recommended as previously created records will not be updated. Consult your implementation team before you attempt to remove or change a currency unit of measure (UOM) after implementation.  The default value is US Dollars.
Cancel Label	[String]	The label that replaces the <b>Cancel</b> action on all form wizards.  A blank value hides the <b>Cancel</b> action.  If the value is set to Cancel, the word is translated for non-US English users on the record form and report manager pages. If set to x, the value is shown regardless of the language settings for the end user. If the value of this property is empty or the property is not in the file, the <b>Cancel</b> button is not displayed.  The default value is x.
CONTEXT_PATH	[Path]	The application context path that accesses the IBM TRIRIGA application. The first character must be /. If you revise this property, you must also revise the enterprise archive (EAR) application.xml file.  The default value is /.
SecurityScopeCacheTime Gap	[Number]	The frequency at which the Security Scope Cache is refreshed in minutes.  The default value is 20.
DataRefreshTime	[Number]	The frequency at which the portal data is refreshed in minutes.  The default value is 5.
SSO	N, Y	If set to Y, the environment runs in single sign-on (SSO) mode.  If set to Y, when you log out of IBM TRIRIGA, the session is ended by closing the browser or browser tab used to access IBM TRIRIGA.  The default value is N.

Property	Values	Description
SSO_BACKING_SERVER_PORT	[Number]	The port number that is used by the back-end server. If the SSO server port does not match the back-end server port, this property must be set.  The default value is -1. If -1 or any other negative value is set for this property, then the port number that is set for the front-end server is also set for the back-end server port.
SSO_REMOTE_USER	N, Y	If set to Y, the request.getRemoteUser() method is used to sign in. The user name must exactly match the user name that is created in IBM TRIRIGA.  When the value of SSO_USER_PRINCIPAL is Y, set SSO_REMOTE_USER to N.  The default value is Y.
SSO_USER_PRINCIPAL	N, Y	If the system is configured to append the User Principal Name (UPN) to the HTTP header, set this property to Y.  If set to Y, the HTTP header parameter <code>UserPrincipal</code> is used, and the user name is retrieved by calling the request.getUserPrincipal().getName() method.  When the value is Y, set the value of the <code>SSO_REMOTE_USER</code> property to N.  The default value is N.
SSO_REMOVE_DOMAIN_NAME	N, Y	If set to Y, the prefixed or appended domain name is removed from the directory server user name that is passed by using the SSO_REMOTE_USER property.  The default value is Y.  If user names contain a domain name when passed from the directory server and user names in IBM TRIRIGA contain only the user name, set this property to Y.  If user names contain a domain name when passed from the directory server and user names in IBM TRIRIGA include the domain name, set this property to N.

Property	Values	Description
SSO_REQUEST_ATTRIBUTE _NAME	[headername], sm_user, [username], [\$WSRU]	The name of the property that is inserted into the HTTP header whose value is the IBM TRIRIGA user name.  The value cannot be blank.  Example 1: For use with SiteMinder, set  SSO_REQUEST_ATTRIBUTE_NAME=sm_user  Example 2: For use with SAML SSO and
		WebSphere Application Server standalone or WebSphere Application Server Liberty, set
		SSO_REQUEST_ATTRIBUTE_NAME=\$WSRU
		This property is case sensitive. Use the requestTest.jsp page to check the correct parameter name. When not in use, it must be set to a non-blank value.
		If the user name is stored in a distinct HTTP attribute variable, set <b>SSO_REMOTE_USER</b> to N, and set this property to the HTTP attribute name.
		In some systems, you can define the variable name in which the user name is located. In this case, set this property to the variable name in your system.
		The default value is headername.
SSO_DISABLE_UNAUTHORIZED _STATUS	N, Y	The unauthorized.jsp page sends an HTTP Error 401 response in the HTTP Header.
		If set to Y, the header response is disabled.
		If you want the HTTP Error 401 response sent, set this property to N.
		The default value is N.
USERNAME_CASE_SENSITIVE	N, Y	If set to Y, sign-in user names are case-sensitive.
		If you want to authenticate without case sensitivity, set this property to N.
		The default value is Y.
SSO_SINGLE_SIGN_OUT _REDIRECT_URL	[URL]	Define to redirect users to a single sign out URL.
		If the SSO parameter is set to Y and this parameter is left blank, the window will close on exit.
		If the SSO parameter is set to N and this parameter is left blank, the user will be directed to the default login page.

Property	Values	Description
ALTERNATE_RESOURCE _DIRECTORY	[Path]	The path to the alternative sign-in page resource directory, for example, C:\pathToTRIRIGA\userfiles\alt.
ALTERNATE_INDEX_HTML	[File name]	The file name of the alternative sign-in page, for example, index.html
ALTERNATE_UX _LOGIN_VIEW	[Name]	The name of an alternate login view for UX applications.
DocumentWorkflow Traversal	N, Y	If set to Y, document permissions are handled with a custom workflow.
		The default value is N.
DEFAULT_TITLE	[String]	Sets the default title for the IBM TRIRIGA application.
SHOW_URL_ON_PORTAL	N, Y	If set to Y, portal queries display URL text.
_QUERY		The default value is Y.
PORTAL_CLOSE_LOGOUT	N, Y	If set to Y, the user is logged out when the portal window closes.
		The default value is Y.
FULL_HELP_OBJECT	N, Y	If set to Y, the full Help business object is shown when you click the <b>Help</b> link.
		If set to N, the Notes section of the Help business object is shown.
		The default value is Y.
REPORT_HEADER_COLUMN	Name, Title	Set this property to show the name or title of the report.
		The default value is Title.
REPORT_MEMORY_USAGE _LIMIT	[Whole number from 0 to 100], [Blank]	The maximum percentage of available server memory that can be used while a user report is running. This limit does not apply to System Reports or Community Reports; it applies to My Reports only.
		If a user sees a query error "There are not enough resources available to run the report", then the query is the likely cause. However, it is also possible that other concurrent processes used memory while the query was assembling its results.
		Valid values are 0 to 100. The specific values of 0 and 100 disable any enforced limit and allow a single query by one user to run the server out of memory. An empty value or an invalid value is treated as a default value.
		The default value is 35.
MOD_NAME_ON_WIZARD	N, Y	If set to Y, the module name shows in the title bar of a record wizard.
		The default value is N.

Property	Values	Description
PORTAL_MY_TIMESHEET	N, Y	If set to Y, the <b>My Timesheet</b> link displays wherever the <b>My Timesheet</b> link can be displayed.
		The default value is N.
ANALYZE_META_DATA _TABLES	N, Y	If set to Y, metadata tables are analyzed during the flat data conversion process.
		The default value is Y.
RUNVALIDATOR	no, yes	If set to yes, the validator runs when you upgrade from TRIRIGA 8i to the TRIRIGA Application Platform 2.x.
		The default value is yes.
Reserve	N, Y	If set to Y, the IBM TRIRIGA Workplace Reservation Manager application is enabled.
		The default value is N.
EXCHANGE_ROOT_PATH	[String]	Sets the Microsoft Exchange server path for IBM TRIRIGA Workplace Reservation Manager appointments.
		The default value is exchange.
EXTERNAL_MAIL_SERVER _USERNAME	[String]	The user name for integrating with Microsoft Exchange and IBM TRIRIGA Workplace Reservation Manager.
		This value can be plain text or encrypted. For information about the encryption tool, see the <i>IBM TRIRIGA Application Platform 3 Administrator Console User Guide.</i>
EXTERNAL_MAIL_SERVER _PASSWORD	[String]	The password for integrating with Microsoft Exchange and IBM TRIRIGA Workplace Reservation Manager.
		This value can be plain text or encrypted. For information about the encryption tool, see the <i>IBM TRIRIGA Application Platform 3 Administrator Console User Guide.</i>
TRIRIGA_RESERVE_SUB _DOMAIN	[String]	The IBM TRIRIGA subdomain for the Microsoft Exchange server. This value determines which emails are forwarded to IBM TRIRIGA. The resources that are managed in IBM TRIRIGA must have a contact to forward to in this subdomain.
	FO: 1	For example, reserve.tririga
EXCHANGE_DOMAIN	[String]	The IBM TRIRIGA domain for the Microsoft Exchange server.
		For example, tririga.com

Property	Values	Description
TRIRIGA_RESERVE_SMTP _ROOT	[Path]	The simple mail transfer protocol (SMTP) root directory that is created when the Reserve SMTP Agent is started. If the directory exists, the IBM TRIRIGA process must have write access to the directory.  For example:  On Microsoft Windows: c:\tririga\install\userfiles\smtp\in\ On UNIX: /tririga/install/userfiles/smtp/in/
TRIRIGA_RESERVE_OUTLOOK _TAB_LABEL	[String]	The label that is displayed when a user connects the Microsoft Outlook client to the IBM TRIRIGA application server.
		For multi-byte support, you must Unicode-escape your values according to the Java specification.
		For example, TRIRIGA Reserve
SMTP_CLIENT_TIMEOUT	[Number]	The timeout of the SMTP endpoint in minutes.
		For example, 10.
SMTP_KEEP_EMAIL	N, Y	Determines whether to keep the email after SMTP processing by iCalendar.
		If set to Y, then the environment keeps the email after processing. Use Y only when SMTP processing is being debugged.
		If set to N, then the environment deletes the email after processing.
SMTP_PORT	[Number]	The port that is used by the Reserve SMTP Agent for incoming SMTP traffic.
		If the value is anything other than 25, then the administrator must route the SMTP traffic to that port value. This value is the port on which IBM TRIRIGA listens for SMTP traffic.
		For example, 25.
SMTP_SUBJECT_PREFIX	[String]	When an outgoing email from IBM TRIRIGA is sent, this string will be prefixed to the Subject of the message. This is so you can tell the difference between Development, Test, and Production environments.
		For example, [Dev].
		The default value is blank.
INCOMING_MAIL _AGENT_SLEEP_TIME	[Number]	Incoming Mail Agent sleep time, measured in seconds.
		For example, 5.
		The default value is 5. This parameter must be set to a minimum value of 1.

Property	Values	Description
CUSTOM ERROR PAGE	N, Y	If set to Y, enables your custom error page.
0001011.11011702		If set to N, a default error page is used.
		The default value is N.
CUSTOM_ERROR_PAGE_PATH	[Path]	The path of the custom error page.
EXCLUDE_CHARACTERS	[String]	List of characters or strings to exclude from fields, which are separated by spaces. Used to avoid characters that can be treated as a script for cross-site scripting (XSS).
		For example, < > & {
ALLOWED_CHARACTERS	[String]	List characters or strings that are allowed in fields, which are separated by spaces. Regular expression characters must be escaped. For example, to allow the character?, enter \\?  For example, \\? & \\(\\\)
ENFORCE_CHARACTER _RESTRICTIONS_FOR _RECORDS	N, Y	If set to Y, the special character restrictions that are defined in the EXCLUDE_CHARACTERS and ALLOWED_CHARACTERS properties are enforced for record publish names. An error occurs if the user tries to save a record with a publish name that includes a character in the EXCLUDE_CHARACTERS property.  The default value is N.
TABLE_SIZE_CHECK_FOR _ORACLE	N, Y	If set to Y, the platform checks the Oracle Database to see whether the table space block size exceeds 8K bytes.  The default value is N.
ErrorHandlerStrategy .MessageResetMinutes	[Number]	The number of minutes the platform waits before it clears duplicate attention messages. When cleared, duplicate attention messages with counts greater than 1 show in a log entry.  The default value is 60.
SYSTEM_DEFAULT_TIMEZONE	[String]	Time zone that is used if the <b>Time Zone</b> field in the record is blank and the user ID is not available, such as application notifications.  The default value is America/Los_Angeles.
SHOW_MY_PROFILE_LINK	N, Y	This controls whether the My Profile Link is
		shown in the My Links portal section.
		The default value is Y.
SHOW_PREFERENCES_LINK	N, Y	This controls whether the Preferences Link is shown in the top navigation.  If set to Y, the "Welcome, [name]" text in the welcome bar becomes a link that the user can click to open the My Profile record of that user.
		The default value is N.

Property	Values	Description
USE_PROJECT_SECURITY	N, Y	Use this property to add project security with the application security that governs records that are returned in queries and accessed through forms.  If set to Y, the user access to a record is controlled by the project security. This security is applied along with the other layers of security that control record access.  The default value is N.
ENEADCE CHT LEVEL OHEDV	N, Y	
ENFORCE_GUI_LEVEL_QUERY _SECURITY	IN, 1	Use this property to control form-level security in reports and queries.  If set to Y, the platform enforces the Security Group settings for the logged in user while a query is running. If the user does not have access to the records that are queried, no results are returned.
		The default value is N.
ENFORCE_REPORT_ACCESS _SECURITY	N, Y	Use this property to have security control whether report or query links are visible to the user. IBM TRIRIGA 10 implementations must set this value to Y and implementations of older versions must set this value to N.  If set to Y, license security and security group security control whether a user sees a report link.  If set to N, security does not control whether a user sees a report link.  The default value is Y.
USE_AUTO_COMPLETE_IN _LOCATOR_FIELD	N, Y	If set to Y, autocomplete is available to users in every locator field for which it is configured. For more information about autocomplete for a locator field, see <i>Application Building for the IBM TRIRIGA Application Platform 3</i> .  The default value is Y.
USE_AUTO_COMPLETE_IN _SMART_SECTION	N, Y	If set to Y, autocomplete is available to users in every single-record smart section for which it is configured. For more information about autocomplete for a single-record smart section, see <i>Application Building for the IBM TRIRIGA Application Platform 3</i> .  The default value is Y.
AUTO_COMPLETE_MIN_CHAR	[Number]	The minimum number of characters a user must type to trigger autocomplete.
		The default value is 3.

Property	Values	Description
DRAWING_REPROCESSING _AS_NEEDED	N, Y	If set to Y, at server startup, the platform checks drawings to see whether any require reprocessing and reprocesses the drawings that need it.  If set to N, at server startup, the platform does not check drawings to see whether any require reprocessing.
		The default value is Y.
GRAPHICS_SECTION _LOGGING_LEVEL	ERROR, INFO, WARN	Sets the client-side logging level for graphics sections.  The default value is ERROR.
PDF_EXPORT_GRAPHIC _STROKE_WIDTH_OVERRIDE	[Blank]	Overrides all stroke (line) widths when a graphics section is exported to a .pdf file. On some larger-scale drawings, the width of lines can look thick when zoomed into the .pdf file at a high magnification. This property can be used to resolve that issue by setting the stroke width to a small constant value such as 0.0000001.  When the value is left blank, the exported .pdf file uses the stroke width that is defined per line in the graphic, which is derived from the line widths as published from the CAD drawing.  The default value is blank with no value specified.
ALLOW_PASSWORD_AUTO_ COMPLETE	N, Y	If set to Y, auto completion of login password is available.  The default value is Y. If no value is specified, this property defaults to Y.
OSLC_MYPROFILE_ RESOURCE	[Profile Name]	The ID of the OSLC resource that represents the My Profile business object.  The default value is triMyProfileRS.
OSLC_BASE_ URI	http:// hostname: port/oslc.	Use this property to define the base URI for OSLC.
OSLC_TRANSACTION_ RETENTION_DAYS	[Days]	The number of days the transaction records are kept. Transaction records are then truncated using smart object delete. Transaction records are physically removed from the database by the object cleanup process.
OSLC_DEFAULT _NAMESPACE	http:// hostname /ns/ism/ smarter_ physical_ infra structure#	Default OSLC namespace.
MASTER_DETAIL_ RECORD_VIEW _TYPE	POPUP, INLINE	Use this property to control how records are displayed in Master Detail navigation targets when clicked.

Property	Values	Description
SNMP_AGENT_PORT	[Number]	The port used in the SNMP Agent for incoming SNMP traps.
		The default value is 161.
SNMP_COMMUNICATION _PROTOCOL	[UDP,TCP]	The IP protocol to use in the SNMP Agent for incoming SNMP traps.
		The default value is UDP.
UNSUCCESSFUL_LOGIN _ATTEMPT	[Number]	How many unsuccessful login attempts are allowed before the account is locked out.
		The default value is -1, which disables this feature.
DOUBLE_GROUPING _FORMAT_PATTERNS	[Character]	The list of decimal format patterns that require double grouping formatting. Characters are separated using semicolons.
		For example, ##,##,00;##,##.##.##;#,##,###.00;#,##,###.##
SHOW_TOTAL _CURRENCY_INDICATOR	N,Y	Enable the currency indicator in the total row of queries. When set to N, the total row of a query does not display the current indicator.
		The default value is N.
VIRUS_SCAN _ENABLED	TRUE,FALSE	Scan for viruses when a file is uploaded to the system.
		The default value is FALSE.
VIRUS_SCANNER _IP_ADDRESS	[IP Address]	IP address of the virus scanner server. This property requires a value if the VIRUS_SCAN_ENABLED enabled property is set to TRUE.
VIRUS_SCANNER _PORT	[IP Address]	Port used by the virus scanner server. This property requires a value if the VIRUS_SCAN_ENABLED enabled property is set to TRUE.
SYSTEM_SECTION_ADD _ACTION_STYLE	[LINK LIGHT_ BUTTON DARK_ BUTTON]	Determines the style of the form section action "Show Add". The default value is LIGHT_BUTTON.
SYSTEM_ACTION_STYLE		Determines the style of links within an Application, which includes the Refresh action in Places such as the Project Tasks section on the Schedule tab of projects. The default value is LIGHT_BUTTON.

Property	Values	Description
CHART_EXPORT_SERVER	[Host name or IP address]	Specifies the AnyChart Export Server to use for handling the conversion of a chart to a JPG, PDF, or PNG when "Save as JPG", "Save as PDF", or "Save as PNG" is selected from the chart. If this property is not set, export.anychart.com will be used. See the following documentation for details on setting up an AnyChart Export Server: http://docs.anychart.com/7.12.0/Common_Settings/Server-side_Rendering.  Note: In the referenced documentation, the step detailed in the "How to Set the Path to Export Server" section is completed by setting the CHART_EXPORT_SERVER property. For example: http://localhost:2000
REP_HISTORY_AGE _CLEANUP	[Number of days]	Specifies how many days to wait before deleting report history. The default value is 365.
OM_AUDIT_TRAIL _ENABLED	TRUE,FALSE	Determines if the OM_PKG_HEADER record header for an object migration package should be kept in the database for audit purposes, or deleted from the database. The default value is FALSE.
OM_AUDIT_TRAIL _RETENTION_DAYS	[Number of days]	Specifies how many days to wait before removing metadata of deleted objects from the database. This value must be set to a whole number greater than 0. The default value is 365.
IBM_SOFTWARE _SUPPORT_URL	[URL]	Software support site. For example, http://www.ibm.com/software/support/
IBM_PLANETWIDE _PHONE_DIRECTORY _URL	[URL]	Worldwide contact directory. For example, http://www.ibm.com/planetwide/
IBM_US_TRIRIGA _SUPPORT_EMAIL _URL	[Email address]	Support contact email address. For example, iot_support@myrep.ibm.com
PRESERVE_IMAGE _HEIGHT_WIDTH _QUERY_SECTION	N,Y	Determines how an image smaller than 50 pixels in height and width is displayed inside a query section when it is attached to a TRIRIGA record image field. When set to 'Y', the original height and width of the image is used when it is displayed in a query. This property does not affect the display of an image in other areas of the application.
CALENDAR_EVENT _MAX_OCCURRENCES	[Number of occurrences]	Set the maximum number of occurrences when creating a recurring booking. The greater the number of occurrences set for this variable, the less performance you get on this process.

In previous releases of IBM TRIRIGA, a viewer was required to view Scalable Vector Graphics (SVG) content. The **SVG\_VIEW\_TYPE** property specifies which application, the Adobe SVG Viewer plug-in, or the IBM TRIRIGA SVG Viewer Applet, renders SVG content. Adobe support for its SVG Viewer plug-in ended January 1, 2009. IBM TRIRIGA now provides the native ability to view SVG content; therefore, the **SVG\_VIEW\_TYPE** property is no longer used.

Property	Values	Description
TREE_PAGING_SIZE	[Number]	The maximum number of child records that are shown in the hierarchy tree for Location, Organization, Geography, Classification, Cost Code, and newly created hierarchical trees. The application includes the child records of the root node in the count.  The default value is 1000.
REBUILD_HIERARCHIES_ON _CACHE_REFRESH	[Valid module names]	Controls which additional hierarchy modules are rebuilt automatically when the hierarchy tree cache is cleared in either the admin console or when the Platform Maintenance Scheduler runs.  The following modules will always be rebuilt automatically:  Geography  Organization  Location  The value of this property is a comma separated list of module names, for example, Document, Classification.

# **Projects**

Property	Values	Description
AUTO_PROJECT _ASSOCIATION _RESTRICTION	[String], [Blank]	Controls the automatic creation of record-level associations between new records and the current Capital Project.
		If set to an association name, such as "Contains", the platform creates that specific record-level association automatically. This association definition must be defined from the Capital Project to the business object of the records that are being created in that project.
		If set to blank (with no value specified), when records are created in a non-default project (or company level), the platform creates all record-level associations automatically. These associations correspond to the association definitions that are defined between the Capital Project business object and the business object of the newly created record.
		If the association definition does not exist from the Capital Project to the business object of the created record, no record-level association is created automatically.
		The value is case-sensitive and must be identical to the value defined in the Data Modeler. The property includes the following typical values:  • "Contains" for IBM TRIRIGA 10 and IBM TRIRIGA 9 applications.  • "Associated To" for IBM TRIRIGA 8i applications.
		The default value is Contains.
RECORD_PROJECT _CONTAINMENT	N, Y, [Blank]	Controls how the platform decides the project context of a record.
		If set to Y or blank, the platform drives project behavior that is based on the project context of the current record. This context helps provide consistent record interactions, especially when a record in one project is opened within the portal context of a different project.
		If set to N, the platform drives project behavior that is based on the portal project context.
		The default value is Y.
SMARTQUERY_RESULT_SIZE _LIMIT	N, Y	Enables the Run Dynamic Query feature in Business Connect.
		The default value is Y.

Property	Values	Description
RUN_DYNAMIC_QUERY _ENABLED	[Number]	The maximum number of query results that can be used in a smart query section. This maximum sets a threshold so that the results of a query do not get so large that the query section is unable to render.
		The default value is 500.
ENFORCE_REQUIRED _VALIDATION	N, Y	Establishes when the platform conducts the required field validations.  If set to Y, when a user moves from tab to tab, the platform does not check whether all required fields on the tab are specified. However, the platform still conducts field validations (for example, isNumeric). On state transitions, the platform checks required fields.
		In addition, if set to Y, this property ensures that a record cannot be created unless all required fields are populated, regardless of the tab. This behavior also occurs in IBM TRIRIGA Connector for Business Applications where in previous releases only the required fields on the first tab were validated. This change has the potential to cause previously working integrations to fail. To resume the previous behavior, set this property to N.
		If set to N, when a user moves from tab to tab, the platform checks that all required fields on the tab are specified. The platform also conducts field validations.
		The default value is Y.
MAX_FORM_ACTION_NUMBER	[Number]	Sets the maximum number of actions that are displayed on a form before the platform puts the excess actions into the overflow button.
		The platform does not count the <b>Cancel</b> action and the overflow button when it determines how many actions to display. The platform puts all secondary actions and normal actions that exceed this number into the overflow button.
		The default value is 4.
SESSION_HISTORY _TRACKING	ALL, NONE, WEB_USER	Indicates which user sessions are logged to the SESSION_HISTORY table.
		If set to WEB_USER, user sessions from IBM TRIRIGA Connector for Business Applications are not logged to the SESSION_HISTORY table.
		The default value is ALL.

Property	Values	Description
ENABLE_PROFILE_ROW _LEVEL_SECURITY	N, Y	Controls user security access to My Profile records.
		If set to Y, the platform uses the Access All Profiles field in the group of the user to determine whether the user can access the My Profile record from another user. Additionally, the user's group controls the user access to the My Profile form and access to tabs, sections, actions, and other form elements.
		If set to N, the user has administrator access to the user's own My Profile record. If a user tries to access the My Profile record from another user, the platform applies standard group access controls.
		The default value is Y.
BIRT_NESTED_TABLE_IN _FOOTER_CLEANUP	FIX, ERROR, DISABLED	The BIRT framework has changed how it handles parameter bindings for nested tables inside a parents footer row. If the table binds to the row of the parent, the value is no longer accessible.
		Reports can be preprocessed at report runtime to handle this framework update in one of three ways.
		FIX: The report design is updated automatically to use a workaround to run the report normally.
		ERROR: The report fails and generates a detailed error message. Use this value to identify reports that need to be refactored.
		DISABLED: The report is not modified. Use this value if report processing causes errors with other reports. All reports run as normal, but affected reports can return incorrect results.
BIRT_MEMORY_USAGE_LIMIT	[Whole number from 0 to 100],	The maximum percentage of available server memory that can be used while the query results of a BIRT report are assembled.
	[Blank]	If the memory requirement for such a task exceeds the limit, the query yields an error because of insufficient resources. The query is the likely cause of the error. However, it is also possible that other concurrent processes used memory while the query was assembling its results.
		Valid values are 0 to 100. The specific values of 0 and 100 disable any enforced limit and allow a single query by one user to run the server out of memory. An empty value or an invalid value is treated as a default value.
		The default value is 35.

Property	Values	Description
MEMORY_MANAGED_PROCESS _POLLING_FREQUENCY	[Number]	The number of milliseconds that the platform waits between polls of memory managed processes. An example of a memory managed process is running BIRT reports.  The default value is 1000, which equals 1
		second.
BIRT_PROCESS_SERVER _HOST_NAME	[Host name or IP address]	The host name or IP address of the BIRT process server. Configure this value to offload the processing of BIRT reports to a separate process server.
		For example:
		• ProcessServer
		• processserver.domain.com
		• 10.1.1.1
		If this value is blank, all BIRT processing is done on the application server.
BIRT_PROCESS_SERVER _PORT	[Number]	The port to send BIRT requests for processing. This value must be configured to offload the processing of BIRT reports. This port corresponds to the value of the BIRT_PROCESS_SERVER_LISTENING_PORT property on the BIRT process server.
		Leave this value blank to process BIRT reports on the application server.
BIRT_PROCESS_SERVER _LISTENING_PORT	[Number]	Configuring this port enables this server as a BIRT process server. The server listens for BIRT requests on this port.
		For example, 47074.
ALLOWED_URL_FOR _REDIRECT	[List of URLs]	The list of URLs or external sites to allow for redirect. The URLs are separated by spaces.
		IBM TRIRIGA blocks redirections to URLs that are not internal to IBM TRIRIGA. To allow a redirection to an external URL, enter that URL in the list.
		For example, http://ibm.com

Property	Values	Description
ALLOW_ETL_DETERMINE_DB _CONNECTIONS	N, Y	Allows the "Extract, Transform, and Load" (ETL) processes to determine whether or not to use multiple database connections.
		If set to Y, then the value of "Use Unique Connections" on the ETL determines whether to use one connection (On) or multiple connections (Off). Setting "Use Unique Connections" to Off in the ETL can improve performance for long-running ETLs, but can cause the application server to run out of database connections for large ETLs with lots of steps that access the database. In this case, it might be necessary to increase the maximum database connections for the application server.
		If set to N, then the platform automatically sets "Use Unique Connections" to On when the ETL is running. Therefore only one database connection is used by the ETL.
		The default value is N.
SESSION_WARNING_ENABLED	N, Y	Allows an alert message to be displayed to a user whose session is about to expire.
		If set to Y, then the session expiration redirects the browser to a session expiration page.
		If set to N, then the session expiration redirection is disabled.
		This property enables or disables the alert message only; it does not configure the session expiration. The session expiration timeout is configured in your application server software. For example, for Liberty profiles, you can edit the server.xml file located in the tririga/wlp/usr/server/tririgaServer directory. Update the httpSession invalidationTimeout value, measured in seconds.
		The default value is N.
SESSION_WARNING _THRESHOLD	[Number]	If the value of the SESSION_WARNING_ENABLED property is set to Y, then this threshold property allows the alert message to be displayed at a specific number of minutes before the session is set to expire.
		This property configures the threshold time for the alert message only; it does not configure the session expiration. The session expiration timeout is configured in your application server software.
		The default value is 2.

Property	Values	Description
OOTB_G11N_EXPORT_APP _VERSION	[String]	Inserts a value or description of the IBM TRIRIGA application version in the file header of the instance data export.
		For example, 10.3.1.
COMPANY_FILE_UPLOAD _EXCLUDE_EXTENSIONS	[Valid file extensions]	Used for image uploads. Restricts file uploads of image files according to their file extensions. Separate the file extensions in the list with commas.
		For a looser restriction, use this property. For a tighter restriction, use the COMPANY_FILE_UPLOAD_INCLUDE_EXTENSIONS property. If both properties are used, then the COMPANY_FILE_UPLOAD_INCLUDE_EXTENSIONS property takes precedence. If neither property is used, then file uploads are not restricted.
		For example, .exe, .js, .sh
		The default value is .exe
COMPANY_FILE_UPLOAD _INCLUDE_EXTENSIONS	[Valid file extensions]	Used for image uploads. Restricts file uploads of image files according to their file extensions. Separate the file extensions in the list with commas.
		For a looser restriction, use the <b>COMPANY_FILE_UPLOAD_EXCLUDE_EXTENSIONS</b> property. For a tighter restriction, use this property. If both properties are used, then this property takes precedence. If neither property is used, then file uploads are not restricted. This property does not cover Document Manager file uploads.
		For example, .png, .bmp, .jpeg
IMPORT_CONTENT_EXCLUDE _EXTENSIONS	[Valid file extensions]	Used for document uploads. Restricts file uploads according to their file extensions. Separate the file extensions in the list with commas.
		For a looser restriction, use this property. For a tighter restriction, use the IMPORT_CONTENT_INCLUDE_EXTENSIONS property. If both properties are used, then the IMPORT_CONTENT_INCLUDE_EXTENSIONS property takes precedence. If neither property is used, then file uploads are not restricted.
		For example, .exe, .js, .sh
		The default value is .exe

Property	Values	Description
IMPORT_CONTENT_INCLUDE _EXTENSIONS	[Valid file extensions]	Used for document uploads. Restricts file uploads according to their file extensions. Separate the file extensions in the list with commas.  For a looser restriction, use the IMPORT_CONTENT_EXCLUDE_EXTENSIONS property. For a tighter restriction, use this property. If both properties are used, then this property takes precedence. If neither property is used, then file uploads are not restricted. This property does not cover Document Manager file uploads.  For example, .doc, .docx, .pdf
MAXIMUM_UPLOAD_FILE _SIZE_MEGABYTES	[Number]	Restricts the size of a file that a user can upload to IBM TRIRIGA. This property should be set to an integer value that represents the maximum upload file size in megabytes.  Valid values must be whole integers greater than 0.  The default is 20. If no value is set the system will automatically restrict the maximum upload to the default value of 20 megabytes.
WS_RELIABLE_MESSAGING	N, Y	Enables (Y) or disables (N) the Web Services Reliable Messaging Protocol (http://schemas.xmlsoap.org/ ws/2005/02/rm/). Set the value to Y to enable. The default is N.
WS_RM_INACTIVITY _TIMEOUT	[Number]	The amount of time that must pass without receiving a message for the Reliable Message sequence to be considered terminated due to inactivity. This property applies only when the WS_RELIABLE_MESSAGING property is enabled.  Specify a value in milliseconds.  The default is 600000, which equals 10 minutes.
WS_RM_BASE _RETRANSMISSION _INTERVAL	[Number]	The interval at which an acknowledgment is received by the Reliable Message source for a given message. This property applies only when the WS_RELIABLE_MESSAGING property is enabled. Specify a value in milliseconds.  The default is 4000, which equals 4 seconds.
WS_RM_ACKNOWLEDGMENT _INTERVAL	[Number]	The interval at which the Reliable Message destination sends asynchronous acknowledgments. This property applies only when the WS_RELIABLE_MESSAGING property is enabled.  Specify a value in milliseconds.  The default is 2000, which equals 2 seconds.

Property	Values	Description
WS_RM_DELIVERY _ASSURANCE_TYPE	AtMostOnce, AtLeastOnce, ExactlyOnce	The delivery assurance type of the Reliable Message. This property applies only when the WS_RELIABLE_MESSAGING property is enabled.  The default is AtMostOnce.
WS_RM_DELIVERY _ASSURANCE_IN_ORDER	N, Y	Enables (Y) or disables (N) the delivery assurance "in order" type of the Reliable Message. This "in order" assurance type can be combined with the delivery assurance type that is specified by the WS_RM_DELIVERY_ASSURANCE_TYPE property. Set the value to Y to enable.  The default is N.
GANTT_STRICT _MODE	TRUE,FALSE	If set to TRUE, strict enforcement of the As Soon As Possible constraint is enabled. Project behavior is the same as with the deprecated Gantt Java-based applet in previous releases.  GANTT_STRICT_MODE=TRUE forces all first tasks (tasks without incoming dependencies) to start directly on either the Planned Project Start Date or Planned Project End Date depending on the value that is specified for Calculate Project From. All next tasks are moved left or right to be as close as possible to their ancestors and to not violate any dependencies or constraints.  If set to FALSE, all first tasks (tasks without incoming dependencies) are moved left as little as possible. Planned Task Start Date and End Date are honored and determine where the task instead of the As Soon as Possible constraint. The next tasks are moved left only to correct dependencies. The next tasks need do not need to be close to their ancestors.  The default is FALSE.
DEFAULT_CHART _COLORS	Commadelimited list of hexadecimal color values in RRGGBB format, for example, 326496, bac95a, 8c2c0e, e8c473	Chart colors can be configured using both the color preferences specified in your profile section, and values defined for the DEFAULT_CHART_COLORS property.
TINYMCE_HTML _EDITOR_ENABLED	TRUE,FALSE	Show or hide the HTML button in Notes fields. When enabled, clicking the HTML button opens the TinyMCE HTML Source Editor.  The default is TRUE.

Property	Values	Description
AVAILABILITY _SECTION_ROW _LIMIT	[Number]	Specifies the maximum number of rows the availability section will display. If there are more rows to be displayed, the availability section will alert the user of the limit.
		This limit is to ensure reasonable performance and memory usage when using the Availability section. The maximum value accepted is 500 rows.
		The default value is 50.
USE_AVAILABILITY _APPLET	TRUE,FALSE	Enables or disables the legacy style Availability section that uses an applet. When disabled, the HTML5 with JavaScript library is used to present Availability information.
		The default is TRUE.
ALLOW_REVERSE _ASSOCIATION	TRUE,FALSE	Enables or disables the use of reverse associations during queries.
		The default is TRUE.
WEATHER_API_KEY	[String]	Holds the license key for The Weather Channel API. The property is used by the triplat-weather UX components.
SHOW_HELP_AND _SUPPORT_LINKS	TRUE,FALSE	Enables or disables the Help and Support links on the IBM TRIRIGA main page. To enable these links, set the value to TRUE.
		The default is FALSE.
HONOR_DOCUMENT _PERMISSIONS_MODEL _FOR_DOWNLOAD	TRUE,FALSE	Checks the document permissions model when a user clicks a document record download link.
ok_bolinesab		When set to TRUE, a user or groups ability to download a document must be set explicitly on the permissions tab of each document record that is created.
		When set to FALSE, a user or group can download a record regardless of the group or user permissions set on the permissions tab.
		The default is FALSE.
AVAILABILITY_SECTION _ROW_LIMIT	[Number]	Limits the maximum number of results when rendering the Availability section.
		If you set this value too high, performance will be impacted when rendering. Very large values will cause memory issues. Update the backing reserve queries to reduce results or design filters that keep the number of record results limited.
		The default is 50 rows. If the value is set to 0, -1, or any other invalid value, the default of 50 will be used. Any value above the maximum value of 500 will be set to 500 instead.

Property	Values	Description
ENABLE_CONCURRENT _AVAILABILITY	TRUE,FALSE	Enables or disables the ability to process reserve queries concurrently.
		The default is TRUE.
CONCURRENT_AVAILABILITY _POOL_SIZE	[Number]	If ENABLE_CONCURRENT_AVAILABILITY is set to TRUE, this property determines the maximum number of system wide threads that will be used in processing availability.
		The default is 50.
CONCURRENT_AVAILABILITY _REQUEST_BATCH_SIZE	[Number]	If ENABLE_CONCURRENT_AVAILABILITY is set to TRUE, this property determines the maximum number of system wide threads that each availability request can use to process availability.
		The default is 10.
WA_UPLOAD_POLL _INTERVAL	[Number]	The amount of time, in minutes, to wait between polling Watson Analytics to check on the status of a dataset upload job.
REPORT_CASE _SENSITIVE		If set to FORCE_CASE_INSENSITIVE, queries Ewith Text values in the Where clause sort in case insensitive order. This setting is the legacy behavior.  If set to NATIVE_DB_CASE_SORT, queries with Text values in the Where clause sort according to the native database settings.  The default is FORCE_CASE_INSENSITIVE.
ALLOW CANTT SCHEDULED	TDITE ENICE	
ALLOW_GANTT_SCHEDULER _UPDATE_ACTUALS	TRUE,FALSE	When set to TRUE, the Gantt scheduler updates Actual Start, End, Working Hours, and Duration values based on the Planned Start date and Actual Percent Complete fields. This business logic is similar to the Task Forms.  The default is TRUE, which reflects the legacy behavior.
		Algorithm:
		• If Actual Percent Complete = 100%, set Actual Start, End, Duration, Working Hours to Planned Start, End, Duration, Working Hours.
		• If Actual Percent Complete > 0, set Actual Start, End, Duration, Working Hours to Planned Start, 0, 0, 0.
		• If Actual Percent Complete = 0, set Actual Start to Planned Start if Actual Start > 0, else set to 0 and set Actual End, Duration, Working Hours to 0, 0, 0.
		When set to FALSE, the Gantt scheduler does not update Actual values if the Actual Start Date is > 0. If Actual Start date is not set, the default behavior is followed.

Property	Values	Description
PERFORMANCE_ANALYZER _MAX_FILE_SIZE _IN_MB	[Number]	Limits the maximum file size in megabytes that the Performance Analyzer allows when processing or uploading log files.
		The property is used to prevent large files from being processed. The larger the file size, the slower the loading of the logs and rendering of the Performance Analyzer form. To minimize the file size, process only specific user scenarios with the Performance Analyzer, particularly when using the SQL and Extended Formula logging, which generate more data than other categories.  The default is 50 MB.

## **CMIS** settings

Property	Values	Description
ENABLE_CMIS	Y, N	Set to Y if the installation uses a CMIS-supported ECM to manage documents within TRIRIGA.  Set to N if the installation uses TRIRIGA Document Manager to manage documents.
		The default value is N.
CMIS_URL	[URL]	The URL of the CMIS server for the AtomPub protocol.
		Leave this property blank if CMIS is not enabled.
CMIS_USER	[string]	The user name of the CMIS server.
		Leave this property blank if CMIS is not enabled.
CMIS_PW	[string]	The password for the CMIS server.
		The password must be encrypted.
		Leave this property blank if CMIS is not enabled.
CMIS_STORE	[store_name]	The name of the ECM document store that holds the TRIRIGA documents.
		Leave this property blank if CMIS is not enabled.
CMIS_ROOT	[folder name]	The ECM folder that is the root for all TRIRIGA documents.
		Leave this property blank if CMIS is not enabled.

## Related information:

□ IBM TRIRIGA Application Platform Compatibility Matrix

## TRIRIGAWEBDYNAMIC.properties

To adjust the IBM TRIRIGA web application version, open the TRIRIGAWEBDYNAMIC.properties file.

## Web dynamic properties

Property	Values	Description
TririgaApplication Version		The version of the IBM TRIRIGA software that is installed. This required value is displayed by the Help subsystem.  For example, 3.0.

## TRIRIGAWEBLOGICPOOL.properties

To adjust the Oracle WebLogic Server connection pool properties, open the TRIRIGAWEBLOGICPOOL.properties file.

### **Connection pool properties**

Property	Values	Description
/jdbc/local/DataSource -TRIRIGA-default	[Valid WebLogic Server pool]	This value must match a connection pool that is configured on the WebLogic Server.  For example, jdbc:weblogic:jts:DefaultPool
/jdbc/local/DataSource -TRIRIGA-content	[Valid WebLogic Server pool]	This value must match a connection pool that is configured on the WebLogic Server.  For example, jdbc:weblogic:jts:ContentPool

## **TRIRIGADB.**properties

To adjust the IBM TRIRIGA database connection properties, open the TRIRIGADB.properties file.

Property	Values	Description
data_dbuser	[String]	User used to connect to the database.
		This value can be set to either an encrypted or unencrypted value.
data_dbpassword	[String]	Password for the user used to connect to the database.
		This value can be set to either an encrypted or unencrypted value.
data_dbname	[String]	Name of the database.
data_data_tblspace	[String]	The name of the data table space that is used to create tables in the data schema.
		For example, a typical value is TRIDATA_DATA.
data_datafile	[String]	Database file name for the data table space.
		For example, a typical value is tridata_data01.dbf.

Property	Values	Description
data_datasize	[Number]	Size of the data table space database, measured in MB.
		For example, a typical value is 2500.
data_index_tblspace	[String]	The name of the index table space that is used to create tables in the data schema.
		For example, a typical value is TRIDATA_INDX.
data_indxfile	[String]	Database file name for the index table space.
		For example, a typical value is tridata_indx01.dbf.
data_indxsize	[Number]	Size of the index table space database, measured in MB.
		For example, a typical value is 2500.
data_bufferpool_name	[String]	The name of the buffer pool used by the TRIRIGA database.
		For example, a typical value is TRIRIGABUFFERPOOL.
mbcs_support	TRUE,FALSE	Support multibyte character sets in Microsoft SQL Server.
		This value is set by the TRIRIGA Application Platform installation program. Do not change the value of this property directly in the file.
mbcs_collation	[String]	Collation setting for the Microsoft SQL Server database.
		The collation setting must include support for case and accent sensitivity.
		For example, a typical value is Latin1_General_CS_AS.
		This value is set by the TRIRIGA Application Platform installation program. Do not change the value of this property directly in the file.
upgrade_sort_area_size	[Number]	Specifies in bytes the maximum amount of memory that Oracle uses for hash joins.
		This setting is used during upgrade only.
upgrade_hash_area_size	[Number]	Specifies in bytes the maximum amount of memory that Oracle uses to sort.
		This setting is used during upgrade only.
upgrade_enable_parallel_	TRUE,FALSE	Enable parallel DML handling for Oracle.
dm1		This setting is used during upgrade only.
<u> </u>	1	

Property	Values	Description
upgrade_trace_level	0,1,2,4,8,12	Set Oracle trace levels for upgrade scripts.
		0 - no statistics
		1 - basic statistics CURSOR, PARSE, EXEC, FETCH ERROR, SORT UMAP, ERROR, UMAP, STATS and XCTEND. This is the same as setting sql_trace=true.
		2 - same as level 1
		4 - same as level 1 except adds BIND section.
		8 - same as level 1 except with wait events.
		12 - same as level 1 but includes binds and waits events. Trace file name will look like: orcl10_ora_nnnn_upgrade_level12.trc if the upgrade_trace_level = 12
		This setting is used during upgrade only.
DB2_TABLES_OUTSIDE_TA	A <b>ISHES</b> BACE	Use this setting to resolve an issue in TRIRIGA Application Platform 3.5.0 and 3.5.1 where IBM DB2 tables are created in a default table space and not the TRIRIGA table space.  Set to SKIP_UPGRADE to prevent the upgrade
		script from running.
		Set to a comma separated list of table to be skipped. For example, if you purposely have a table, like DM_CONTENT in a different table space, you would set DB2_TABLES_OUTSIDE_TABLESPACE=DM_CONTENT
		This setting is used during upgrade only.

## License files

IBM TRIRIGA controls the usage of its various products with license files. Starting with IBM TRIRIGA Application Platform 3.2, IBM TRIRIGA distributes a separate license for each product.

Each license file grants access to its respective functions when it is assigned to a user. The license files by themselves do not enforce license count restrictions. Each license is governed by its respective software license agreement. The license file names are in the format LICENSE IBM TRIRIGA [productname].properties; for example, LICENSE\_IBM\_TRIRIGA\_Application\_Platform.properties.

The license matrix is delivered in the software. It is available at **Tools** > Administration > License Manager. The License Manager includes a List View and a Matrix View.

The license matrix is IBM PROPRIETARY and CONFIDENTIAL and its disclosure to you shall be governed by the terms of the IBM Agreement for the Exchange of Confidential Information found at http://www-05.ibm.com/support/operations/ files/pdf/aeci\_ca\_en.pdf, or the applicable confidentiality agreement signed between IBM and your company. IBM TRIRIGA is providing the license matrix as a courtesy to you under the condition that you treat the information with the utmost confidence. Under no circumstances may you distribute or allow use of the license matrix outside of your organization without first obtaining IBM's express

written consent. The license matrix should not be construed as a definitive list of functionality licensed by the you; it is simply a proxy for the limited functionality that you have actually licensed, but your actual licenses are set forth in separate agreements between IBM and your company. The license matrix is provided for informational purposes only without warranty of any kind, does not contain contractual obligations, does not constitute a software, product or services warranty, and is subject to change without notice.

### Before IBM TRIRIGA Application Platform 3.2

Before IBM TRIRIGA Application Platform 3.2, IBM TRIRIGA distributed one license file named TRIRIGALICENSE.properties. If you have an existing TRIRIGALICENSE.properties file, you can continue to use it until it expires or until you use a new product.

### License types

This single-file method managed three distinct types of licenses: (1) Concurrent User, (2) Named User, and (3) Enterprise.

License type	Description
Concurrent User	The Concurrent User license offered a pool of licenses to limit the number of users who signed into the application at any one time. Although there might be hundreds of unique user accounts in the application, the number of concurrent users was restricted by the Concurrent User license.
Named User	The Named User license assigned each seat in the license to a uniquely named user. Users did not share licenses. If a customer needed extra user accounts, the customer was required to upgrade the license.
Enterprise	The Enterprise license did not restrict the number of users in a company by allowing an unlimited number of users.

#### IBM TRIRIGA Application Platform 3.2 and later

After the IBM TRIRIGA Application Platform installation, your [tririga\_root]\config\licenses directory must contain either your LICENSE\_IBM\_TRIRIGA\_[productname].properties files or your TRIRIGALICENSE.properties file, but not both.

After a new installation, copy your license files into the <code>[tririga\_root]\config\licenses</code> directory. After an upgrade installation, verify that your license files were automatically copied into the <code>[tririga\_root]\config\licenses</code> directory.

If you use the LICENSE\_IBM\_TRIRIGA files, do not use the TRIRIGALICENSE file. If you use the TRIRIGALICENSE file, do not use the LICENSE\_IBM\_TRIRIGA files. If you are using WebSphere Application Server and LICENSE\_IBM\_TRIRIGA files, set up valid resource URLs for all of your licenses. If you are using WebSphere Application Server and the TRIRIGALICENSE file, verify that the resource URL points to the correct location.

After you upgrade to the LICENSE\_IBM\_TRIRIGA files, you cannot return to the previous TRIRIGALICENSE file. When you start the application server for the first time after you upgrade to the LICENSE\_IBM\_TRIRIGA files, the application attempts to swap user licenses to the LICENSE\_IBM\_TRIRIGA license set. For this process to be successful, it is important that all of your LICENSE\_IBM\_TRIRIGA files exist in the <code>[tririga\_root]\config\licenses</code> directory and that all user changes are complete.

Verify that all asynchronous workflows are completed before you restart the application server with the LICENSE IBM TRIRIGA files.

All application servers, that is IBM TRIRIGA installs, that access a database must have the same license set. In other words, all licenses that a customer is entitled to that they want to deploy, including Install license types, must be installed on all IBM TRIRIGA installs that access a IBM TRIRIGA database.

### **Deprecated licenses**

Several licenses that were contained in the TRIRIGALICENSE file were deprecated with the LICENSE\_IBM\_TRIRIGA files. The Enterprise licenses are no longer bundled, but IBM TRIRIGA distributes their equivalent licenses for individual products.

Former Enterprise license	Equivalent IBM TRIRIGA licenses	
Facility Management Enterprise	(1) Real Estate Manager, (2) Facilities Manager, and (3) Workplace Operations Manager	

#### **Available licenses**

IBM TRIRIGA distributes the following LICENSE\_IBM\_TRIRIGA files for individual products.

License files
LICENSE_IBM_TRIRIGA_Anywhere_Workplace_Operations.properties
LICENSE_IBM_TRIRIGA_Application_Builder.properties
LICENSE_IBM_TRIRIGA_Application_Platform.properties
LICENSE_IBM_TRIRIGA_CAD_Integrator_Publisher.properties
LICENSE_IBM_TRIRIGA_Capital_Projects_Manager.properties
LICENSE_IBM_TRIRIGA_Connector_for_Business_Applications.properties
LICENSE_IBM_TRIRIGA_Connector_for_Offline_Forms.properties
LICENSE_IBM_TRIRIGA_Facilities_and_Real_Estate_Management_on_Cloud_Approvals_and _Reporting.properties
LICENSE_IBM_TRIRIGA_Facilities_and_Real_Estate_Management_on_Cloud_Enterprise .properties
LICENSE_IBM_TRIRIGA_Facilities_and_Real_Estate_Management_on_Cloud_Occasional .properties
LICENSE_IBM_TRIRIGA_Facilities_and_Real_Estate_Management_on_Cloud_Self_Service .properties
LICENSE_IBM_TRIRIGA_Facilities_Manager.properties
LICENSE_IBM_TRIRIGA_Facility_Assessment.properties
LICENSE_IBM_TRIRIGA_Integrated_Workplace_Manager.properties
LICENSE_IBM_TRIRIGA_Mobile.properties
LICENSE_IBM_TRIRIGA_Portfolio_Data_Manager.properties
LICENSE_IBM_TRIRIGA_Real_Estate_Environmental_Sustainability_Impact_Manager .properties
LICENSE_IBM_TRIRIGA_Real_Estate_Environmental_Sustainability_Manager .properties
LICENSE_IBM_TRIRIGA_Real_Estate_Manager.properties

License files
LICENSE_IBM_TRIRIGA_Request_Central.properties
LICENSE_IBM_TRIRIGA_Strategic_Facility_Planning.properties
LICENSE_IBM_TRIRIGA_Workplace_Operations_Manager.properties
LICENSE_IBM_TRIRIGA_Workplace_Performance_Management_Enterprise .properties
LICENSE_IBM_TRIRIGA_Workplace_Performance_Management_Facilities .properties
LICENSE_IBM_TRIRIGA_Workplace_Performance_Management_Operations .properties
LICENSE_IBM_TRIRIGA_Workplace_Performance_Management_Projects .properties
LICENSE_IBM_TRIRIGA_Workplace_Performance_Management_Real_Estate.properties
LICENSE_IBM_TRIRIGA_Workplace_Reservation_Coordinator.properties
LICENSE_IBM_TRIRIGA_Workplace_Reservation_Manager.properties
LICENSE_IBM_TRIRIGA_Workplace_Reservation_Manager_for_Small_Installations .properties

## **Context path**

During the IBM TRIRIGA Application Platform installation, you can define an alternative application context path that accesses the IBM TRIRIGA application. The default value is a slash (/). By defining an alternative context path, you can deploy IBM TRIRIGA as a non-root application.

If you defined a non-root context path, then after installation is complete, you must use the corresponding URL address to access the IBM TRIRIGA application. For example, if you specified that the context path was /tri, then you must access the IBM TRIRIGA application with the URL address of http://[hostname:port]/tri, where [hostname:port] is the specific value for your application server environment.

If you have multiple installations, it might be valuable to define a different context path for each installation. For example, /tridev, /tritest, and /triprod.

# Connection pools

Connection pools contain a cached set of database connections that can be used for incoming database connection requests. You configure a connection pool to accommodate the number of concurrent users and transaction load expected, Depending on your environment, the connection pool settings in one or more files must be configured for correct connectivity to the database. Connection pool names are case-sensitive.

The recommended setting for minimum connections is 10. The recommended setting for maximum connections is 100. A setting of 100 maximum connections is common for a JVM that is not expected to exceed 500 concurrent users. You can modify the connection pool setting on the data source defined for IBM TRIRIGA.

Connection pool settings	File location
Oracle WebLogic Server pools	[tririga_root]\config\TRIRIGAWEBLOGICPOOL.properties  For example, C:\Tririga\config\ TRIRIGAWEBLOGICPOOL.properties
Oracle Database trace levels	[tririga_root]\config\TRIRIGAMIDDLEWARE.properties For example, C:\Tririga\config\ TRIRIGAMIDDLEWARE.properties

http://www-01.ibm.com/support/knowledgecenter/SSEQTP\_8.5.5/ com.ibm.websphere.base.iseries.doc/ae/udat\_conpoolset.html

## **Cross-site scripting filters**

Cross-site scripting (XSS) filters are defined in the TRIRIGAWEB.properties file with the EXCLUDE\_CHARACTERS and ALLOWED\_CHARACTERS properties. By default, typical XSS characters are filtered.

XSS filters are applied in the following cases: (1) the user name and password input fields in the sign-in page, (2) the input fields in the IBM TRIRIGA Application Platform builder tools, and (3) the published name input fields in forms.

XSS filter properties	Description
EXCLUDE_CHARACTERS	This property contains a list of characters or strings to exclude from fields, which are separated by spaces. For example: < > & {
ALLOWED_CHARACTERS	This property contains a list of characters or strings to allow in fields, which are separated by spaces. Regular expression characters must be escaped with a double backslash (\\). For example, ? must be specified as \\?. To allow the following four characters ? & ( ), specify \\? & \\( \\ \\)

# Configuring agent processes

Certain IBM TRIRIGA agents or agent processes must be configured when they apply to your particular implementation. Before you configure the process server to run agents, first complete the IBM TRIRIGA Application Platform installation on the process server.

## **Business process agents**

The IBM TRIRIGA Application Platform agents are business process agents that conduct the automated work for the IBM TRIRIGA applications. When the platform identifies an event that requires an agent, the platform places the event into a queue where the agent can retrieve and process it.

Business process agent	Description
Platform Maintenance Scheduler	This agent conducts data cleanup and runs an analysis on the database. This agent removes all data in the state of null, and removes DataConnect (DC) jobs and staging table entries that are obsolete or completed. This agent also cleans up the completed workflow instances that do not have any user-operable tasks (such as user tasks and approval tasks) within the workflow.

Business process agent	Description
Data Import Agent	This agent looks for all tab-delimited files that are uploaded and imports the data into the platform.
DataConnect (DC) Agent	This agent looks for DataConnect (DC) jobs in the Job Control table that are ready to run. When the agent finds a job, it creates an appropriate smart object for the job. Then the agent posts an asynchronous workflow event to initiate the workflow that pulls the external data into the IBM TRIRIGA database tables.
Extended Formula Agent	This agent looks for and processes extended formulas.
Formula Recalc Agent	This agent recalculates formulas as needed in the platform.
Incoming Mail Agent	This agent downloads mail from a Post Office Protocol 3 (POP3) server or Internet Message Access Protocol (IMAP) server and translates them into email message records.
Object Migration Agent	This agent migrates business objects from one environment to another environment.
Object Publish Agent	This agent publishes business objects in the platform.
Report Queue Agent	This agent retrieves queued report requests, processes the report, and notifies the user.
Reserve SMTP Agent	This agent receives and processes reservation e-mails sent by Microsoft Exchange. This Simple Mail Transfer Protocol (SMTP) receiver service allows Microsoft Exchange to communicate with IBM TRIRIGA and allow it to manage resources in Reserve. A Microsoft Exchange send connector is configured to forward any email address with the reservation-specific subdomain to the IBM TRIRIGA application server that runs this SMTP agent.
Scheduler Agent	This agent looks for and processes all scheduled and recurring events in the platform.
Workflow (WF) Agent	This agent processes queued workflow events and the asynchronous workflows that are registered for those events.
Workflow (WF) Notification Agent	This agent looks for and processes notifications in the platform, including those notifications to be sent at a scheduled time.

#### Administrator console

Before you configure the process server to run agents, first complete the IBM TRIRIGA Application Platform installation process on the process server. Then, open the Agent Manager in the IBM TRIRIGA administrator console to configure and manage agents.

You can independently stop and start each agent from the Agent Manager in the IBM TRIRIGA administrator console. If you want to prevent an agent from starting on the process server, you can configure that agent in the AGENTS\_NOT\_ALLOWED property of the TRIRIGAWEB.properties file. Then, restart the process server for changes in the TRIRIGAWEB.properties file to take effect.

However, if an agent is stopped, parts of the IBM TRIRIGA application might not function with the same behavior. For example, if the Workflow (WF) Agent is stopped, the platform does not run any logic that is defined by an asynchronous workflow. Instead, the platform holds each event in a queue that the WF Agent picks up when it is restarted.

For more information, see the *IBM TRIRIGA Application Platform 3 Administrator Console User Guide*.

### **Attaching Microsoft Outlook messages**

Microsoft Exchange converts a sent Microsoft Outlook message (.msg file) and any attached messages (.msg files) into Multipurpose Internet Mail Extensions (MIME) format. However, the IBM TRIRIGA Incoming Mail Agent is not designed to recognize attachments in MIME format. Instead of attaching Microsoft Outlook .msg messages to another .msg message, you have two alternative options.

#### **Procedure**

1. Attach the file.

Method	Action
Microsoft Outlook	Save the .msg attachment as a Microsoft Outlook file template (.oft file). Then, attach the .oft file to the main .msg message that you are delivering in Microsoft Outlook.
Microsoft Outlook Web App	Attach the .msg file to the main email that you are delivering in the Microsoft Outlook Web App (OWA).

2. Send the message or email.

## Configuring the SMTP port in Linux

Linux does not allow root users to bind port traffic to ports 1024 and below. However, the simple mail transfer protocol (SMTP) port property of the TRIRIGAWEB.properties file has a default value of port 25. If you are running Linux, you must configure the reserve SMTP agent to listen to a custom port instead of the default port 25.

### Before you begin

You must be an IBM TRIRIGA administrator. Run the commands in the following procedure as a root user.

#### **Procedure**

1. Update your firewall to open the port above port 1024 by adding the following lines to your /.../sysconfig/iptables file:

```
    -A OUTPUT -p tcp -s serverIP -d 0/0 --dport Port_Above_1024
    -m state --state ESTABLISHED -j ACCEPT
    -A INPUT -s 0/0 -d serverIP -m state --state NEW,ESTABLISHED
    -p tcp --dport Port Above 1024 -i eth0 -j ACCEPT
```

2. Restart your firewall:

/.../init.d/iptables restart

3. Open port 25 for forwarding:

/sbin/iptables -A FORWARD -p tcp --destination-port 25 -j ACCEPT;

4. Forward port 25 to your custom port above 1024:

```
/sbin/iptables -t nat -A PREROUTING -j REDIRECT -p tcp --destination-port 25 --to-port Port Above 1024
```

5. To verify that port 25 is forwarding, start the IBM TRIRIGA application server so that it binds to your custom port, and run a telnet command: telnet *yourServer* 25

6. If you do not receive a successful response, forward port 25 to a different custom port (step 4).

#### What to do next

This task does not permanently configure the port. If the Linux server is restarted or the IP tables service is reset from a firewall modification, then the configuration is dropped. To reconfigure the port, you must forward port 25 to your custom port (step 4) again.

## **Configuring Tivoli Directory Integrator for IBM TRIRIGA**

If you plan to use TRIRIGA Real Estate Environmental Sustainability you must configure TRIRIGA to use Tivoli® Directory Integrator to run the needed ETL job items.

For instructions on how to configure TRIRIGA for Tivoli Directory Integrator, see the IBM TRIRIGA wiki.

### Post installation

After a successful installation, configure IBM TRIRIGA as required.

Multicultural support, also known as globalization, is the process of organizing an application so that it can be configured to work in different countries and in different languages. You can use IBM TRIRIGA Application Platform to translate messages and any other text content that appears into the language you want.

For more information, search for *TRIRIGA localization* in the IBM Knowledge Center.

IBM TRIRIGA can be configured to use Single Sign On (SSO) technology if SSO has been configured in your environment. After the appropriate properties are configured, IBM TRIRIGA can accept tokens issued by application servers for SSO. IBM Support can assist with configuring IBM TRIRIGA properties for SSO. However, due to the number of supported products, technologies, and configurations supported by IBM TRIRIGA, IBM Support cannot assist in the configuration of SSO within your environment.

# Chapter 3. Workflow cleanup log

When you start the application server or process server for the first time after you install IBM TRIRIGA Application Platform, a workflow validation process is initiated. This process identifies and reports any issues that might keep the workflows from running as expected. The log report is named WorkflowCleanup.log.

The workflow validation process runs for only one time, when you start the server for the first time after installation. The process reports any issues with published workflows that require a user action to resolve, and any issues that are repaired automatically. After the process is completed, you can review the log report to understand which workflows were updated and which workflows might need your attention.

The log report is written to the log directory of the IBM TRIRIGA installation. For example, on Windows, C:\Tririga\log\WorkflowCleanup.log is the typical location.

## Log format

The format of the log report can contain as many as three main sections. The first section indicates that the process ran and completed. The second section lists any issues and related workflows that cannot be repaired automatically. The third section lists any issues and related workflows that were repaired automatically.

Similar issues are listed together. Within an issue, the workflows are ordered by module, business object, and workflow name. Many of the issues provide more information to help you locate the specific step that needs review or repair. A workflow might be listed more than one time, depending on what issues were found and what repairs were made. It is also possible for a workflow that was retired by the process (because of an irreparable issue) to contain more issues than what was reported.

### Log example

The following sample comes from a WorkflowCleanup.log report, and highlights the three main sections:

```
Workflow cleanup and repair processing pass 1.
Workflow cleanup and repair processing pass 2.
Workflow cleanup and repair completed in 2 passes.
```

### The following problems could not be completely repaired.

```
Review the identified workflow(s) and the action taken (if any) and resolve any remaining problems to assure correct workflow execution.

Condition expression is invalid. Review and correct the expression.

Workflow:19124805.14 Module=exModule1 BO=-Any- Name='exModule1 - condition'
Invalid Expression[p0 == == 1] Step:0 Start(1) 'Start'
Retired the workflow because of missing step definitions that could not be repaired.

Workflow:10485177.0 Module=exModule1 BO=exBO
Name='exModule1 - PRE-CREATE - initialize'
Information about missing definition: Step:100033 Switch(14)
Parent Step:100030 Modify Records(28) 'Update Examples'
```

```
The following problems were repaired.
```

Review the identified workflow(s) and the resolution to assure correct workflow execution.

Removed the entry from  $WF\_LOOKUP$  because the workflow is not in a published

Workflow:19122518.0 Module=exModule1 BO=-Any- Name='A New Workflow' Retired the workflow because there isn't a corresponding entry in WF LOOKUP.

Workflow:19122236.2 Module=exModule1 BO=-Any- Name='Copy of A New Workflow' Flow control value was invalid. Set step to normal flow (non-swapped).

Review flow and verify this is correct.

Workflow:19139030.0 Module=exModule1 BO=-Any- Name='exModule1 - Workflow 2'

Invalid flow value was 'REPORT' Step:206635 Break(21)

Retired the workflow because its Module could not be found.

Workflow:19122928.1 Module=<23549> BO=-Any- Name='Example Map Source to Section' Step definition added for End step.

Workflow:10179388.0 Module=exModule1 B0=exB02

Name='Delete associated BO Values'

Added the required End step structure and definition information.

Workflow:18412.1 Module=exModule2 B0=exB03

Name='exB03 - Add Values'

Changed step with missing definition to a No-Op.

Workflow:12034842.1 Module=exModule1 BO=-Any-

Name='exModule1 - exUpdate - Record Update'

Information about missing definition: Step:1000112 Call Workflow(38)

Parent Step: 1000100 Fork (13)

Workflow:19111379.6 Module=exModule2 B0=exB03

Name='exModule2 - exB03 - Populate File'

Information about missing definition: Step:205341 Populate File(36)

Parent Step:0 Start(1) 'Start'

## Reported issues

The log report might identify issues that the process cannot repair automatically. When the process cannot repair a workflow automatically, it typically retires the workflow. You can review this log report to repair any issues in the workflows that your business processes require, and publish the revised workflows.

## Suggested actions

The following issues cannot be repaired automatically. The table shows the issue that is written to the WorkflowCleanup.log file and the corresponding description and suggested actions.

Issue	Description
Condition expression is invalid. Review and correct the expression.	A workflow condition expression is invalid and the expression cannot be processed. At run time, these conditions are treated as though they are blank. For Start conditions, the workflow is started. For Switch conditions, the expression is always true. For Break conditions, the Loop or Iteration is stopped. The information for the workflow lists the expression and the task step in which it is contained. The process leaves the workflow in the published state. The workflow must be revised, the expression must be corrected, and the workflow must be republished.
Retired the workflow because of a block structure error that cannot be repaired.	A block structure within the workflow has a problem that makes it invalid and cannot be repaired by the process. The following task types define block structures: Switch, Loop, Iterator, Fork, and DataConnect. The process retires the workflow. Review the retired workflow and correct any problems. It is possible that a workflow that is listed might not open in the Workflow Builder. If the listed workflow version cannot be opened, then open older versions for review.

Issue	Description
Retired the workflow because of a missing Start step that cannot be repaired.	The workflow is missing the Start task step and cannot be repaired by the process. The process retires the workflow. Review the retired workflow and correct any problems. It is possible that a workflow that is listed might not open in the Workflow Builder. If the listed workflow version cannot be opened, then open older versions for review.
Retired the workflow because of missing Start and End steps that cannot be repaired.	The workflow is missing the Start and End task steps and cannot be repaired by the process. The process retires the workflow. Review the retired workflow and correct any problems. It is possible that a workflow that is listed might not open in the Workflow Builder. If the listed workflow version cannot be opened, then open older versions for review.
Retired the workflow because of a structure error that cannot be repaired.	The step-to-step structure of the workflow has a problem that makes it invalid and the structure cannot be repaired by the process. The process retires the workflow. Review the retired workflow and correct any problems. It is possible that a workflow that is listed might not open in the Workflow Builder. If the listed workflow version cannot be opened, then open older versions for review.
Retired the workflow because of an unknown task type <type-number>.</type-number>	The workflow contains a step with a task type that cannot be understood by the workflow processor. Since the step uses an unknown task type, this condition cannot be repaired by the process. The process retires the workflow. Review the retired workflow and correct any problems. It is possible that a workflow that is listed might not open in the Workflow Builder. If the listed workflow version cannot be opened, then open older versions for review.
Retired the workflow because of missing step definitions that cannot be repaired.	The properties for one or more steps within the workflow cannot be loaded. Since the properties for the step are specific to the logic of the workflow, this condition cannot be repaired by the process. The process retires the workflow. Review the retired workflow and correct any problems. It is possible that a workflow that is listed might not open in the Workflow Builder. If the listed workflow version cannot be opened, then open older versions for review.
Unexpected problem in trying to load the workflow.	This issue covers any problems that do not fit into any of the other categories. The process retires the workflow. Review the retired workflow and correct any problems. It is possible that a workflow that is listed might not open in the Workflow Builder. If the listed workflow version cannot be opened, then open older versions for review.

# **Automatic repairs**

The following issues can be repaired automatically. The table shows the issue that is written to the WorkflowCleanup.log file and the corresponding description and automatic repairs.

Issue	Description
Added the required End step structure and definition information.	Valid workflows require an End task step and one cannot be found. The process adds an End task step to the workflow. Review the workflow to verify that the step was added correctly.

Issue	Description
Changed step with missing definition to a No-Op.	The properties for a task step cannot be loaded. According to past behavior, when the properties for a step cannot be loaded, the step was skipped and processing was continued with the next step. Because the properties for steps other than an End or Stop task are specific to the workflow, the process cannot create them. However, because the step was skipped in the past, the process replaces the task step with a No-Op task step. A No-Op (or No Operation) task step is a task step that does nothing. The log entry provides information about what was replaced so the workflow can be reviewed. Review previous versions of the workflow to determine the purpose of the step and replace the step if necessary. The task types Switch, Fork, Loop, Iterator, and DataConnect cannot be converted to a No-Op step. Missing properties for these task types results in retiring the workflow. (This condition is covered by the table of issues that cannot be automatically repaired by the process.)
Converted obsolete task type step to a No-Op.	Older workflows might contain task steps that were not supported since the Workflow Builder was released in 2005. These obsolete types are most likely to exist in workflows that were originally created with the older non-graphical workflow editor. According to past behavior, the process skipped these task steps and continued to the next step. The process converts these task steps to No-Op steps.
Flow control value was invalid. Set step to normal flow (non-swapped).	Switch and Break task steps contain an internal value that indicates whether the condition must be used as-is or swapped. If the internal value is not valid for either a normal or swapped step, the process replaces it with the value for a normal step. This value is an internally used value and not the condition expression for the step. Review the listed Switch or Break and verify that the step is correct. Swap the step if necessary.
Removed the entry from WF_LOOKUP because the workflow is not in a published state.	An entry for the workflow existed in the WF_LOOKUP table, but the workflow is not currently published. Only published workflows must have an entry in the WF_LOOKUP table, so the entry was removed. The workflow can be published if it is necessary for current business processes.
Retired the workflow because its Business Object could not be found.	The business object for which the workflow is defined does not exist. If the business object does not exist, then this workflow cannot run. The process retires the workflow.
Retired the workflow because its Module could not be found.	The module for which the workflow is defined does not exist. If the module does not exist, then this workflow cannot run. The process retires the workflow.
Retired the workflow because there isn't a corresponding entry in WF_LOOKUP.	The workflow entry in the WF_TEMPLATE table has a status of Published, but there is no entry in the WF_LOOKUP table. Since the WF_LOOKUP table locates workflows at run time, this workflow cannot run. The process changes the status from Published to Retired. The workflow can be published if it is necessary for current business processes.
Step definition added for Block-End step.	The properties for a Block-End task step cannot be loaded. A Block-End task step is the bottom of a Switch or Loop task step. All task steps require valid properties to be run. However, the properties for this task type do not contain any values that are specific to the workflow. The process creates valid properties for them.

Issue	Description
Step definition added for End step.	The properties for an End task step cannot be loaded. All task steps require valid properties to be run. However, the properties for this task type do not contain any values that are specific to the workflow. The process creates valid properties for them.
Step definition added for No-Op step.	The properties for a No-Op task step cannot be loaded. A No-Op task step is a task step that does nothing, but sometimes it is added to a workflow by the Workflow Builder. All task steps require valid properties to be run. However, the properties for this task type do not contain any values that are specific to the workflow. The process creates valid properties for them.
Step definition added for Stop step.	The properties for a Stop task step cannot be loaded. All task steps require valid properties to be run. However, the properties for this task type do not contain any values that are specific to the workflow. The process creates valid properties for them.
Updated the workflow name in WF_LOOKUP.	The name of the workflow in the WF_LOOKUP table does not match the name in the WF_TEMPLATE table. The process repaired this condition by updating the name in the WF_LOOKUP table. Review the name and verify that this name is expected.

## **Notices**

This information was developed for products and services offered in the US. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those

websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample

programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year).

Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. \_enter the year or years\_.

### **Trademarks**

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other product and service names might be trademarks of IBM or other companies.

# Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

## **Applicability**

These terms and conditions are in addition to any terms of use for the IBM website.

#### Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

#### Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

### **Rights**

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

## **IBM Online Privacy Statement**

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at http://www.ibm.com/privacy and IBM's Online Privacy Statement at http://www.ibm.com/privacy/details in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at http://www.ibm.com/software/info/product-privacy/.

# IBM.

Printed in USA