IBM Spectrum Protect Plus Version 10.1.4

Installation and User's Guide



# Note: Before you use this information and the product it supports, read the information in "Notices" on page 297.

# Ninth edition (May 2020)

This edition applies to version 10, release 1, modification 4 of IBM Spectrum Protect Plus (product number 5737-F11) and to all subsequent releases and modifications until otherwise indicated in new editions.

# © Copyright International Business Machines Corporation 2017, 2020.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

# **Contents**

I

Publications	••••••
What's new in Version 10.1.4	• • • • • • • • • • • • • • • • • • • •
Getting involved in product development	
Sponsor user program	
Beta program	
Chapter 1. Product overview	•••••
Product components	
Product dashboard	
Alerts	
Role-based access control	
Replicate backup-storage data	
Offload to secondary backup storage	
IBM Spectrum Protect Plus on IBM Cloud	
IBM Spectrum Protect Plus on AWS	
Chapter 2 Installing IBM Chaptering Dystoct Dive	
Chapter 2. Installing IBM Spectrum Protect Plus	
Product deployment roadmap	
System requirements	
Component requirements	
Hypervisor requirements	
File indexing and restore requirements	
Microsoft Exchange Server requirements	
Db2 <sup>®</sup> requirements	
MongoDB requirements	
Oracle requirements	
Microsoft SQL Server requirements	
Obtaining the IBM Spectrum Protect Plus installation package	
Installing IBM Spectrum Protect Plus as a VMware virtual appliance	
Installing IBM Spectrum Protect Plus as a Hyper-V virtual appliance	
Assigning a static IP address	
Uploading the product key	
Editing firewall ports	
Installing iSCSI initiator utilities	•••••
Chapter 3. Installing and configuring vSnap servers	
Installing vSnap servers	
Installing a physical vSnap server	
Installing a virtual vSnap server in a VMware environment	
Installing a virtual vSnap server in a Hyper-V environment	
Managing vSnap servers	
Adding a vSnap server as a backup storage provider	
Initializing the vSnap server	
Setting vSnap storage options	
Expanding a vSnap storage pool	
=	

	Changing offload throughput rate	59
	vSnap server administration reference	60
	Storage management	61
	Network management	63
	Synchronizing the vSnap Password	64
	Uninstalling a vSnap server	64
	Chapter 4. Getting off to a quick start	
	Start IBM Spectrum Protect Plus	
ı	Manage sites	
	Create backup policies	
	Create a user account for the application administrator	
	Add resources to protect	
	Add resources to a job definition	
	Start a backup job Run a report	
	Chapter 5. Updating IBM Spectrum Protect Plus components	
	Updating the IBM Spectrum Protect Plus virtual appliance	
	Updating vSnap servers	
	Updating the operating system for a physical vSnap server	
	Updating the operating system for a virtual vSnap server	
	Updating a vSnap server	84
	Updating VADP proxies	84
	Applying early availability updates	86
	Chapter 6. Manage SLA policies for backup operations	97
	Creating an SLA policy	
	Editing an SLA policy	
	Deleting an SLA policy	
		00
	Chapter 7. Protecting hypervisors	
	VMware	
	Adding a vCenter Server instance	
	Backing up VMware data	
	Mangaging VADP backup proxies	
	Restoring VMware data	
	Hyper-V	
	Adding a Hyper-V server	
	Backing up Hyper-V data Restoring Hyper-V data	
•	Restoring files	
	Chapter 8. Protecting applications	
	Db2Prerequisites for Db2	
	Adding a Db2 application server	
	e :	
	Backing up Db2 data	
	Restoring Db2 data	
	Exchange Server	
	Prerequisites	
	Privileges	
	Adding an Exchange application server	
ı	Backing up Exchange databases	
	Incremental forever backup strategy	
!	Restoring Exchange databases	
1	Accessing Exchange database files with instant access mode	180

	MongoDB	182
	Prerequisites for MongoDB	
	Adding a MongoDB application server	
	Backing up MongoDB data	
1	Restoring MongoDB data	
•	SQL Server	
	Adding a SQL Server application server	
	Backing up SQL Server data	
1	Restoring SQL Server data	
•	Oracle	
	Adding an Oracle application server	
	Backing up Oracle data	
1	Restoring Oracle data	
	Chapter 9. Protecting IBM Spectrum Protect Plus	
	Backing up the application	
	Restoring the application	
	Managing restore points	
	Deleting IBM Spectrum Protect Plus resources from the catalog	229
	Chantay 10 John and anavations	224
ı	Chapter 10. Jobs and operations	
	Starting jobs	
	Pausing and resuming jobs Canceling jobs	
	Rerunning partially completed backup jobs	
	Backing up a single resource	
	Uploading a script	
	Adding a script to a server	
	Adding a script to a server	230
	Chapter 11. Configuring and maintaining the IBM Spectrum Protec	t Plus system
	environment	=
	Managing secondary backup storage	
	Managing cloud storage	
	Managing repository server storage	
	Managing keys and certificates	
	Managing sites	
	Adding a site	
	Editing a site	
	Deleting a site	
	Managing LDAP and SMTP servers	
	Adding an LDAP server	
	Adding an SMTP server	
	Editing settings for an LDAP or SMTP server	
	Deleting an LDAP or SMTP server	
1	Applying global preferences	
•	Logging on to the administrative console	
	Setting the time zone	
	Uploading an SSL certificate from the administrative console	
	Logging on to the virtual appliance	
	Accessing the virtual appliance in VMware	
	Accessing the virtual appliance in Hyper-V	
	Testing network connectivity	
	Running the Service Tool from a command line	
	Running the Service Tool from a command lineRunning the Service Tool remotely	260

Adding a disk to the virtual appliance	
Adding storage capacity from a new disk to the appliance volume	262
Chapter 12. Managing reports and logs	267
Types of reports	
Backup storage utilization reports	267
Protection reports	
System reports	269
VM Environment reports	270
Report actions	272
Running a report	272
Creating a custom report	272
Scheduling a report	
Collecting and reviewing audit logs for actions	
Enabling the display of alerts in the system log	273
Chapter 13. Managing user access	275
Managing user resource groups	
Creating a resource group	
Editing a resource group	
Deleting a resource group	
Managing roles	
Creating a role	
Editing a role	
Deleting a role	
Managing user accounts	
Creating a user account for an individual user	
Creating a user account for an LDAP group	
Editing a user account credentials	
Deleting a user account	
Managing identities	
Adding an identity	
Editing an identity	
Deleting an identity	
Chapter 14. Licensing overview	287
Software License Metric (SLM) tags	
Integration with IBM License Metric Tool (ILMT)	
Chapter 15. Troubleshooting	289
Collecting log files for troubleshooting	
Chapter 16. Product messages	29′
Message prefixes	
Appendix A. Search guidelines	293
Appendix B. Accessibility	291
Notices	
Glossary	301
Index	303
±11W&\\assaceaeaaaaaaaaaaaaaaaaaaaaaaaaaaaaaa	

# **About this publication**

This publication provides overview, planning, installation, and user instructions for IBM Spectrum Protect Plus.

# Who should read this publication

This publication is intended for administrators and users who are responsible for implementing a backup and recovery solution with IBM Spectrum Protect Plus in one of the supported environments.

In this publication, it is assumed that you have an understanding of the applications that support IBM Spectrum Protect Plus as described in "System requirements" on page 11.

# **Publications**

The IBM Spectrum Protect product family includes IBM Spectrum Protect Plus, IBM Spectrum Protect for Virtual Environments, IBM Spectrum Protect for Databases, and several other storage management products from IBM®.

To view IBM product documentation, see IBM Knowledge Center.

# What's new in Version 10.1.4

IBM Spectrum Protect Plus Version 10.1.4 introduces new features and updates.

For a list of new features and updates in this release and previous Version 10 releases, see <u>IBM Spectrum</u> Protect Plus updates.

New and changed information in this product documentation is indicated by a vertical bar (|) to the left of the change.

# **Getting involved in product development**

You can influence the future of IBM Storage products by sharing your insights with the design and development teams. To get involved, join the sponsor user program or the beta program.

# Sponsor user program

The IBM Storage sponsor user program allows you to work directly with designers and developers to influence the direction of products that you use.

IBM invites you to share your experience and expertise. By joining the program, you can help us to explore, and potentially implement, new product features that are important to you and your business.

Do you use an IBM Storage software product, such as IBM Spectrum Protect Plus?

Are you ready to share your vision?

Then sign up for the sponsor user program to participate in the product innovation process. In addition, as a sponsor user, you can preview upcoming storage releases and participate in beta programs to test new product features.

To join the sponsor user program or to obtain additional information, complete the following form:

IBM Storage Sponsor User

Your information will remain confidential and will be used by the IBM design and development teams only for product development purposes.

# Beta program

The IBM Spectrum Protect Plus beta program gives you a first glance at upcoming product features and a chance to influence design changes. You can test new software in your environment and have a direct voice in the product development process.

The beta program attracts a broad range of participants, including customers, IBM Business Partners, and IBM employees.

The program offers the following benefits:

# Gain access to early code and evaluate new product features and enhancements

You get access to the beta code before general availability of the product release to determine whether the new features and enhancements are a good fit for your organization. After the code is downloaded, you can run and validate the new software in your environment. You can then identify and resolve any concerns before the code is available, thus saving time and helping to prevent production issues later. When the code becomes available, you are ready to install it and take advantage of the new capabilities.

# Interact with design and development teams

The product designers, architects, developers, and testers help to plan the beta release and support its participants. These experts can assist you with resolving any issues.

# **Become an IBM reference customer**

After your positive beta experience, IBM invites you to participate in the reference program. The IBM marketing team helps you craft a message to let other potential beta testers know about your success in adopting and using early code.

# **Contact and enrollment information**

You can enroll by completing the IBM Spectrum Protect Plus Beta Program Signup Form.

# Chapter 1. IBM Spectrum Protect Plus overview

IBM Spectrum Protect Plus is a data protection and availability solution for virtual environments and database applications that can be deployed in minutes and protect your environment within an hour.

IBM Spectrum Protect Plus can be implemented as a stand-alone solution or integrated with cloud storage or a repository server such as an IBM Spectrum Protect server to offload copies for long-term storage.

# **Product components**

The IBM Spectrum Protect Plus solution is provided as a self-contained virtual appliance that includes storage and data movement components.

**Sizing component requirements:** Some environments might require more instances of these components to support greater workloads. For guidance about sizing, building, and integrating components in your IBM Spectrum Protect Plus environment, see the <u>IBM Spectrum Protect Plus</u> Blueprints.

The following are the base components of IBM Spectrum Protect Plus:

# **IBM Spectrum Protect Plus server**

This component manages the entire system. The server consists of several catalogs that track various system aspects such as restore points, configuration, permissions, and customizations. There is one IBM Spectrum Protect Plus appliance in a deployment, even if the deployment is spread across multiple locations.

The IBM Spectrum Protect Plus server contains an onboard vSnap server and VMware vStorage API for Data Protection (VADP) proxy server. For smaller backup environments, these servers might be sufficient. However, for larger environments, more VADP proxy servers might be required.

The onboard vSnap server can be used to back up and restore a small number of virtual machines and evaluate IBM Spectrum Protect Plus operations. As your requirements for backing up and restoring data grow, your vSnap storage can be expanded by adding external vSnap servers. By adding external vSnap servers to your environment, you can reduce the load on the IBM Spectrum Protect Plus appliance.

### Site

This component is an IBM Spectrum Protect Plus policy construct that is used to manage data placement in the environment. A site can be physical, such as a data center, or logical, such as a department or organization. IBM Spectrum Protect Plus components are assigned to sites to localize and optimize data paths. A deployment always has at least one site per physical location. The preferred method is to localize data movement to sites by placing vSnap servers and VADP proxies together at a single site. The placement of backup data to a site is governed by service level agreement (SLA) policies.

# vSnap server

This component is a pool of disk storage that receives data from production systems for the purposes of data protection or reuse. The vSnap server consists of one or more disks and can be scaled up (adding disks to increase capacity) or scaled out (introducing multiple vSnap servers to increase overall performance). Each site can include one or more vSnap servers.

# vSnap pool

This component is the logical organization of disks into a pool of storage space, which is used by the vSnap server component. This component is also referred to as a storage pool.

# **VADP** proxy

This component is responsible for moving data from vSphere data stores to provide protection for VMware virtual machines and is required only for protection of VMware resources. Each site can include one or more VADP proxies.

### **User interfaces**

IBM Spectrum Protect Plus provides the following interfaces for configuration, administrative, and monitoring tasks:

# **IBM Spectrum Protect Plus user interface**

The IBM Spectrum Protect Plus user interface is the primary interface for configuring, administering, and monitoring data protection operations.

A key component of the interface is the dashboard, which provides summary information about the health of your environment. For more information about the dashboard, see <u>"Product dashboard" on page 3.</u>

The menu bar in the user interface contains the following items:

Alerts icon	This icon opens the <b>Alerts</b> window. For more information about alerts, see "Alerts" on page 4.
Help icon	This icon opens the online help system.
User menu	This menu shows the name of the user who is logged on. The menu provides access to product information and documentation, logs, and the user sign out option.

# vSnap command-line interface

The vSnap command-line interface is a secondary interface for administering some data protection tasks. Run the **vsnap** command to access the command line interface. The command can be invoked by the user ID serveradmin or any other operating system user who has vSnap admin privileges.

# **Administrative console**

The administrative console is used to install software patches and updates and to complete other administrative tasks such as managing security certificates, starting and stopping IBM Spectrum Protect Plus, and changing the time zone for the application.

# **Example deployment**

The following figure shows IBM Spectrum Protect Plus deployed in two active locations. Each location has inventory that requires protection. Location 1 has a vCenter server and two vSphere datacenters (and an inventory of virtual machines) and Location 2 has a single datacenter (and a smaller inventory of virtual machines).

The IBM Spectrum Protect Plus server is deployed in only one of the sites. VADP proxies and vSnap servers (with their corresponding disks) are deployed in each site to localize data movement in the context of the protected vSphere resources.

Bidirectional replication is configured to take place between the vSnap servers at the two sites.




Figure 1. IBM Spectrum Protect Plus deployment across two geographical locations

# **Product dashboard**

The IBM Spectrum Protect Plus dashboard summarizes the health of your virtual environment in three sections: **Jobs and Operations**, **Destinations**, and **Coverage**.

# **Jobs and Operations**

The **Jobs and Operations** section shows a summary of job activities for a selected time period. Select the time period from the drop-down list. The following information is shown in this section:

### **Currently Running**

The **Currently Running** section shows the total number of jobs that are running and the percentage of central processor unit (CPU) usage in the IBM Spectrum Protect Plus virtual appliance. This percentage is refreshed every 10 seconds.

To view detailed information about running jobs, click View.

### **History**

The **History** section shows the total number of jobs that were completed within the selected time period. This number does not include running jobs.

This section also shows the success rate for jobs over the selected time period. The success rate is calculated by using the following formula:

100 x Successful Jobs / Total Jobs = Success Rate

Completed jobs are shown by job status:

# Successful

The number of jobs that were completed with no warnings or critical errors.

### **Failed**

The number of jobs that failed with critical errors or that failed to be completed.

### Warning

The number of jobs that were partially completed, skipped, or otherwise resulted in warnings.

To view detailed information job history information, click View.

### **Destinations**

The **Destination** section shows a summary of the devices that are used for backup operations. The following information is shown in this section:

# **Capacity Summary**

The **Capacity Summary** section shows the current usage and availability of the vSnap servers that are available to IBM Spectrum Protect Plus.

To view information about vSnap servers, click View.

### **Device Status**

The **Device Status** section shows the total number of devices that are available for use.

The number of devices that are offline or otherwise unavailable is shown in the **Inactive** field.

The number of devices that are at capacity is shown in the **Full** field.

### **Data Reduction**

The **Data Reduction** section shows data deduplication and data compression ratios.

The data deduplication ratio is the amount of data that is protected compared with the physical space that is required to store the data after duplicates are removed. This ratio represents additional space savings achieved on top of the compression ratio. If deduplication is disabled, this ratio is 1.

# Coverage

The **Coverage** section shows a summary of the resources that are inventoried by IBM Spectrum Protect Plus and the service level agreement (SLA) policies that are assigned to the resources. The following information is shown in this section:

### **Source Protection**

The **Source Protection** section shows the total number of source resources, such as virtual machines and application servers, that are inventoried in the IBM Spectrum Protect Plus catalog. The number of protected and unprotected resources are shown.

This section also shows the ratio of resources that are protected in IBM Spectrum Protect Plus to the total resources, expressed as a percent.

### **Policies**

The **Policies** section shows the total number of SLA policies with associated protection jobs.

This section also shows the three SLA policies that have the highest count assigned resources.

To view detailed information about all SLA policies, click **View**.

# **Alerts**

The **Alerts** menu displays current and recent warnings and errors in the IBM Spectrum Protect Plus environment. The number of alerts is displayed in a red circle, indicating that alerts are available to view.

Click the **Alerts** menu to view the alerts list. Each item in the list includes a status icon, a summary of the alert, the time the associated warning or error occurred, and a link to view associated logs.

**Restriction:** The **Disabled Deduplication** alert is available only if you install IBM Spectrum Protect Plus interim fix 10.1.4.222 or later.

The alert list can include the following alert types:

# Alert types

# Job failed

Is displayed when a job fails.

# Job partially succeeded

Is displayed when a job partially succeeds.

# System disk space low

Is displayed when the amount of free disk space is 10% or less.

# vSnap storage space low

Is displayed when the amount of free disk space is 10% or less.

# System memory low

Is displayed when memory usage exceeds 95%.

# System CPU usage high

Is displayed when processor usage exceeds 95%.

# **Hypervisor VM not found**

Is displayed when the VM is not found.

# Replication storage snapshot locked exception

Is displayed when the replication storage snapshot is locked. Increase replication retention or increase the replication frequency policy.

# Offload storage snapshot locked exception

Is displayed when the most recently offloaded storage snapshot is locked. Increase offload retention or increase the offload frequency policy.

# **SQL** log backup failure

Is displayed when log backup fails for a database.

# **SQL** log **SMO** backup failure

Is displayed when there is a Server Management Object transaction log backup failure.

# **SQL** log size too large

Is displayed when the transaction log size is larger than space available on disk.

# SQL log remaining space low

Is displayed when the transaction log backup staging directory is low on disk space and displays the amount of space remaining.

# Disabled deduplication on storage

Is displayed when deduplication gets disabled and displays the IP of the storage server. This will occur when the vSnap auto disable deduplication table (DDT) option is enabled and the defined size or percentage threshold is exceeded.

# Role-based access control

Role-based access control defines the resources and permissions that are available to IBM Spectrum Protect Plus user accounts.

Role-based access provides users with access to only the features and resources that they require. For example, a role can allow a user to run backup and restore jobs for hypervisor resources, but does not allow the user to complete administrative tasks such as creating or modifying user accounts.

To complete the tasks that are described in this documentation, the user must belong to a role that has the required permissions. Ensure that your user account belongs to a role that has the required permissions before you start the task.

To set up and manage user access, see Chapter 13, "Managing user access," on page 275.

# Replicate backup-storage data

When you enable replication of backup data, data from one vSnap server is asynchronously replicated to another vSnap server. For example, you can replicate backup data from a vSnap server on a primary site to a vSnap server on a secondary site.

# **Enabling replication of backup-storage data**

Enable backup-storage data replication by taking the following actions:

1. Establish a replication partnership between vSnap servers. Replication partnerships are established in the Manage pane of a registered vSnap server. In the **Configure Storage Partners** section, select

another registered vSnap server as a storage partner to serve as the target of the replication operations.

Ensure that the pool on the partner server is sufficiently large enough to hold replicated data from the primary server's pool.

2. Enable replication of backup-storage data. The replication feature is enabled by using backup policies, which are also referred to as service level agreement (SLA) policies. These policies define parameters that are applied to backup jobs, including the frequency of backup operations and the retention policy for the backups. For more information about SLA policies, see <a href="Chapter 6">Chapter 6</a>, "Manage SLA policies for backup operations," on page 87.

You can define the backup storage replication options in the **Operational Protection** > **Replication Policy** section of an SLA policy. Options include the frequency of the replication, the target site, and the retention of the replication.

# Considerations for enabling replication of backup-storage data

Review the considerations for enabling replication of backup-storage data:

- If your environment includes a mixture of encrypted and unencrypted vSnap servers, select **Only use encrypted disk storage** to replicate data to encrypted vSnap servers. If this option is selected and no encrypted vSnap servers are available, the associated job will fail.
- To create one-to-many replication scenarios, where a single set of backup data is replicated to multiple vSnap servers, create multiple SLA policies for each replication site.

# Offload to secondary backup storage

The vSnap server is the primary backup location for snapshots. All IBM Spectrum Protect Plus environments have at least one vSnap server. Optionally, you can offload snapshots from a vSnap server to secondary backup storage.

The following secondary backup storage targets are available for offload operations:

- IBM Cloud Object Storage (including IBM Cloud Object Storage Systems)
- Amazon Simple Storage Service (Amazon S3)
- · Microsoft Azure
- Repository servers (for the current release of IBM Spectrum Protect Plus, the repository server must be an IBM Spectrum Protect server)

These targets support the following storage types. The storage type that you use depends on factors such as your recovery time and security goals.

### **Object storage**

Object storage is a method of storing data in which data is stored as discrete units, or objects, in a storage pool or repository that does not use a file hierarchy but that stores all objects at the same level.

Object storage is an option when you offload data to an IBM Spectrum Protect server or a cloud storage system. When snapshot data is offloaded to object storage, a full copy is created during the first offload operation. Subsequent copies are incremental and capture cumulative changes since the last offload.

Offloading snapshots to object storage is useful if you want relatively fast backup and recovery times and do not require the longer-term protection, cost, and security benefits that are provided by tape or cloud archive storage.

# Tape or cloud archive storage

Tape storage means that data is stored on physical tape media or in a virtual tape library. Tape storage is an option when you offload data to an IBM Spectrum Protect server. By storing tape volumes at a secure, offsite location that is not connected to the internet, you can help to protect your data from online threats such as malware and hackers.

Cloud archive storage is long-term storage method that copies data to one of the following storage services: Amazon Glacier, IBM Cloud Object Storage Archive Tier, or Microsoft Azure Archive.

When you offload data to tape or to a cloud storage system, a full copy of the data is created.

Offloading snapshots to tape or cloud archive storage provides extra cost and security benefits. However, because offloading to these storage types requires a full data copy, the time required to copy data increases. In addition, the recovery time can be unpredictable and the data might take longer to process before it is usable.

For information about how snapshot data is copied to object storage and archival storage for each cloud storage system, see "Cloud requirements" on page 19.

# Adding secondary backup storage and creating backup policies

To offload data to secondary storage, the following actions are required:

Action	How to
To offload data to a repository server  Set up IBM Spectrum Protect Plus as an object client in the IBM Spectrum Protect server environment.  Add the storage to IBM Spectrum Protect Plus.	See "Configuring an IBM Spectrum Protect server as an offload target" on page 243 and "Adding a repository server as a backup storage provider" on page 243.
To offload data to cloud storage, add the storage to IBM Spectrum Protect Plus.	Follow the instructions for your selected storage type:  • "Adding Amazon S3 cloud storage as a backup storage provider" on page 237  • "Adding IBM Cloud Object Storage as a backup storage provider" on page 238  • "Adding Microsoft Azure cloud storage as a backup storage provider" on page 240  • "Adding a repository server as a backup storage provider" on page 243
Create a backup policy that includes the storage.	See "Create backup policies" on page 70.

# **Example deployments**

The following figure shows IBM Spectrum Protect Plus deployed in two active locations. Each location has inventory that requires protection. Location 1 has a vCenter server and two vSphere datacenters (and an inventory of virtual machines) and Location 2 has a single datacenter (and a smaller inventory of virtual machines).

The IBM Spectrum Protect Plus server is deployed in only one of the sites. VADP proxies and vSnap servers (with their corresponding disks) are deployed in each site to localize data movement in the context of the protected vSphere resources.

Bi-directional replication is configured to take place between the vSnap servers at the two sites.

Snapshots are offloaded from the vSnap server at the secondary site to cloud storage for long-term data protection.




Figure 2. IBM Spectrum Protect Plus deployment across two geographical locations with offload to cloud storage

The following figure shows the same deployment as the previous figure.

However, in this deployment, snapshots are offloaded from the vSnap server at the secondary site to IBM Spectrum Protect for long-term data protection.




Figure 3. IBM Spectrum Protect Plus deployment across two geographical locations with offload to IBM Spectrum Protect

# **IBM Spectrum Protect Plus on IBM Cloud**

IBM Spectrum Protect Plus is available as an IBM Cloud for VMware Solutions service, IBM Spectrum Protect Plus on IBM Cloud.

IBM Cloud for VMware Solutions enables you to integrate or migrate your on-premises VMware workloads to the IBM Cloud by using the scalable IBM Cloud infrastructure and VMware hybrid virtualization technology.

IBM Cloud for VMware Solutions provides the following major benefits:

### Global reach

Expand your hybrid cloud footprint to a maximum of 30 enterprise-class IBM Cloud datacenters around the world.

# **Streamlined integration**

Use the streamlined process to integrate the hybrid cloud with the IBM Cloud infrastructure.

# **Automated deployment and configuration**

Deploy an enterprise-class VMware environment with on-demand IBM Cloud Bare Metal Servers and virtual servers by using automated deployment and configuration of the VMware environment.

# **Simplification**

Use a VMware cloud platform without identifying, procuring, deploying, and managing the underlying physical compute, storage, and network infrastructure, and software licenses.

# **Expansion and contraction flexibility**

Expand and contract your VMware workloads according to your business requirements.

# Single management console

Use a single console to deploy, access, and manage the VMware environments on IBM Cloud.

# Available features in IBM Spectrum Protect Plus on IBM Cloud

IBM Spectrum Protect Plus supports both VMware and Microsoft Hyper-V environments.

However, IBM Spectrum Protect Plus on IBM Cloud supports only VMware environments.

This documentation includes topics about features that are specific to Hyper-V. These features are not available if you are using IBM Spectrum Protect Plus on IBM Cloud.

The current version of IBM Spectrum Protect Plus and IBM Spectrum Protect Plus on IBM Cloud might not be the same. To find the documentation for the version of IBM Spectrum Protect Plus on IBM Cloud that you are using, go to the online product documentation and select the product version.

# For more information

For information about how to order, install, and configure IBM Spectrum Protect Plus on IBM Cloud, see the following documentation. An IBMid is required to access the documentation.

- Getting started with IBM Cloud for VMware Solutions
- Components and considerations for IBM Spectrum Protect Plus on IBM Cloud
- Managing IBM Spectrum Protect Plus on IBM Cloud

# **IBM Spectrum Protect Plus on the AWS cloud platform**

IBM Spectrum Protect Plus on the Amazon Web Services (AWS) cloud platform is a solution for users who run IBM Spectrum Protect Plus on premises, but want to protect databases that are running on the AWS cloud

IBM Spectrum Protect Plus on AWS is a hybrid solution in which the IBM Spectrum Protect Plus server is on-premises and the vSnap server is on AWS.

The policy, system administration, access control, and other features of IBM Spectrum Protect Plus are managed and maintained by the on-premises IBM Spectrum Protect Plus server. Data from databases that are on AWS is then stored in the vSnap server that is also on AWS.

# **Deploying IBM Spectrum Protect Plus to AWS**

The IBM Spectrum Protect Plus page on AWS Marketplace provides the AWS CloudFormation templates that are required to deploy the vSnap server to AWS as well as pricing, usage, and support information. Follow the instructions on this page and the IBM Spectrum Protect Plus on the AWS Cloud Deployment Guide to set up your on-premises and AWS environments.

The IBM Spectrum Protect Plus on AWS deployment includes IBM Spectrum Protect Plus version 10.1.3. If you want to use the current version of IBM Spectrum Protect Plus, follow the instructions in <a href="#">Chapter 5,</a> "Updating IBM Spectrum Protect Plus components," on page 81 to complete an upgrade.

# **Chapter 2. Installing IBM Spectrum Protect Plus**

Before you install IBM Spectrum Protect Plus, review the system requirements and installation procedures.

# **Product deployment roadmap**

Follow the roadmap to install, configure, and start using IBM Spectrum Protect Plus.

Action	How to
Ensure that your system environment meets the hardware and software requirements.	See <u>"System requirements"</u> on page 11.
Determine how to size, build, and place the components in your IBM Spectrum Protect Plus environment.	See the IBM Spectrum Protect Plus Blueprints.
Install IBM Spectrum Protect Plus.	See Chapter 2, "Installing IBM Spectrum Protect Plus," on page 11.
If additional vSnap servers are required to support your environment, install and configure the servers.	See Chapter 3, "Installing and configuring vSnap servers," on page 51.
If additional VMware vStorage API for Data Protection (VADP) proxies are required to support your environment, create and configure the proxies.	See "Managing VADP backup proxies" on page 102.
Complete the basic steps to set up and start using IBM Spectrum Protect Plus.	See Chapter 4, "Getting off to a quick start," on page 67.

# **System requirements**

Before you install IBM Spectrum Protect Plus, review the hardware and software requirements for the product and other components that you plan to install in the storage environment.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see <u>technote 2013790</u>.

To determine how to size, build, and place the components that are listed in the specifications in your IBM Spectrum Protect Plus environment, see the IBM Spectrum Protect Plus Blueprints.

# **Component requirements**

Ensure that you have the required system configuration and a supported browser to deploy and run IBM Spectrum Protect Plus.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

IBM Spectrum Protect Plus support for third-party platforms, applications, services, and hardware parallels that of the third-party vendors. When a third-party vendor product or version enters extended support, self-serve support, or end of life, IBM Spectrum Protect Plus supports it at the same level.

### Virtual machine installation

IBM Spectrum Protect Plus is installed as a virtual appliance. Before you deploy IBM Spectrum Protect Plus to the host, ensure that the following requirements are in place:

- vSphere 5.5, 6.0, 6.5, or 6.7
- Microsoft Hyper-V Server 2016, or Hyper-V 2019.

For initial deployment, configure your virtual appliance to meet the following minimum requirements:

- 64-bit 8-core machine
- 48 GB memory
- 536 GB disk storage for virtual machine

Use a Network Time Protocol (NTP) server to synchronize the time zones across IBM Spectrum Protect Plus resources that are in your environment, such as the IBM Spectrum Protect Plus virtual appliance, storage arrays, hypervisors, and application servers. If the clocks on the various systems are significantly out of sync, you might experience errors during application registration, metadata cataloging, inventory, backup, restore, or file restore jobs. For more information about identifying and resolving timer drift, see the following VMware knowledge base article: Time in virtual machine drifts due to hardware timer drift.

# **Browser support**

Run IBM Spectrum Protect Plus from a computer that has access to the installed virtual appliance. IBM Spectrum Protect Plus was tested against the following web browsers. Note that later browser versions might also be supported.

- Firefox 55.0.3
- Google Chrome 60.0.3112 and later
- Microsoft Edge 40.15063/Microsoft EdgeHTML 15.15063 and later

If your screen resolution is less than  $1024 \times 768$  pixels, some items might not fit on the window. Pop-up windows must be enabled in your browser to access the help system and some IBM Spectrum Protect Plus operations.

# **IBM Spectrum Protect requirements**

If you plan to use IBM Spectrum Protect as a repository server for cloud offload operations, ensure that you are using IBM Spectrum Protect V8.1.8.

# **IBM Spectrum Protect Plus ports**

The following ports are used by IBM Spectrum Protect Plus and associated services. Ports that are indicated by "Accept" in the Firewall Rule column use secure connections (HTTPS or SSL).

Table 1. Incoming firewall connections (IBM Spectrum Protect Plus appliance)				
Port	Protocol	Firewall	Service	Description
22	ТСР	Accept	OpenSSH 5.3 (protocol 2.0)	Used for troubleshooting IBM Spectrum Protect Plus
443	ТСР	Accept	A microservice running a reverse-proxy	Main entry point for the client connections (SSL)

Table 1. Incoming firewall connections (IBM Spectrum Protect Plus appliance) (continued)				
Port	Protocol	Firewall	Service	Description
5671	TCP, AMQP	Accept	RabbitMQ	Message framework used to manage messages produced and consumed by the VADP proxy and VMware job management workers. Also facilitates job log management.
8090	TCP	Accept	Administrative Console Framework (ACF)	Extensible framework for system administration functions. Supports plugins that run operations such as system updates and catalog backup or restore operations
8761	TCP	Accept	Discovery Server	Automatically discovers VADP proxies and is used by IBM Spectrum Protect Plus VM backup operations

Table 2. Incoming firewall connections (onboard vSnap server)					
Port	Protocol	Firewall	Service	Description	
111	TCP	Accept	RPC Port Bind	Allows clients to discover ports that Open Network Computing (ONC) clients required to communicate with ONC servers (internal)	
2049	TCP	Accept	NFS	Used for NFS data transfer to and from vSnap (internal)	
3260	ТСР	Accept	iSCSI	Used for iSCSI data transfer to and from vSnap (internal)	

Table 2. Incoming firewall connections (onboard vSnap server) (continued)					
Port	Description				
20048	ТСР	Accept	NFS	Used for NFS data transfer to and from vSnap (internal)	

Table 3. Outgoing firewall connections (IBM Spectrum Protect Plus appliance)				
Port	Protocol	Service	Description	
22	ТСР	OpenSSH 5.3 (protocol 2.0)	Used for SSH communications to remote servers running guest applications components.	
25	TCP	SMTP	Email service.	
389	ТСР	LDAP	Active directory services.	
443	TCP	VMware ESXi Host	ESXi host port for managing operations.	
443	ТСР	VMware vCenter	Client connections to vCenter.	
636	ТСР	LDAP	Active directory services (SSL).	
902	ТСР	VMware NFC service	Network File Copy (NFC) provides a file-type-aware FTP service for vSphere components. By default, ESXi uses NFC for operations such as copying and moving data between datastores.	
5985	ТСР	Windows Remote Management (WinRM)	Hyper-V and guest applications client connections.	
8098	TCP	VADP proxy	Virtual machine data protection proxy.	
8900	ТСР	vSnap	OVA/Installer version of the intelligent storage framework used as a target for data protection operations.	

# vSnap server requirements

A vSnap server is the primary backup destination for IBM Spectrum Protect Plus. In either a VMware or Hyper-V environment, one vSnap server with the name localhost is automatically installed at the time that the IBM Spectrum Protect Plus virtual appliance is initially deployed. In larger backup enterprise environments, more vSnap servers might be required.

Allocate memory based on backup capacity for more efficient deduplication. For more information and sizing guidance, see IBM Spectrum Protect Plus Blueprints.

For initial deployment, ensure that your virtual machine or physical Linux® machine meets the following minimum requirements:

- 64-bit 8-core processor
- 32 GB memory
- 16 GB free space on root file system
- 128 GB free space on a separate file system mounted at the following location: /opt/vsnap-data

The Linux Network Management service must be installed and running.

Optionally, a solid-state drive (SSD) improves backup and restore performance.

- To improve backup performance, configure the pool to use one or more log devices backed by an SSD. Specify at least two log devices to create a mirrored log for better redundancy.
- To improve restore performance, configure the pool to use a cache device backed by an SSD.

# vSnap server virtual machine installation requirements

Before deploying the vSnap server to the host, ensure that the following requirements are in place:

- vSphere 5.5, 6.0, 6.5. or 6.7
- Microsoft Hyper-V 2016 or Microsoft Hyper-V 2019.

# vSnap server physical installation requirements

Beginning with V10.1.3, IBM Spectrum Protect Plus provides functionality that requires the kernel levels supported in RHEL 7.5 and CentOS 7.5. If you must use operating systems earlier than RHEL 7.5 and CentOS 7.5, use IBM Spectrum Protect Plus V10.1.2 for physical vSnap V10.1.2 installations.

The following Linux operating systems are supported for IBM Spectrum Protect Plus V10.1.4 or later physical vSnap server installations:

- CentOS 7.1804 (7.5) (x86\_64)
- CentOS 7.1810 (7.6) (x86\_64)
- RedHat Enterprise Linux 7.5 (x86\_64)
- Red Hat Enterprise Linux 7.6 (x86\_64)

If you are using the following operating systems, use IBM Spectrum Protect Plus V10.1.2 for physical vSnap server V10.1.2 installations:

- CentOS Linux7.3.1611 (x86 64)
- CentOS Linux7.4.1708 (x86 64)
- Red Hat Enterprise Linux 7.3 (x86 64)
- Red Hat Enterprise Linux 7.4 (x86\_64)

# vSnap server ports

The following ports are used by vSnap servers. Ports that are indicated with Accept in the Firewall Rule column use secure connections (HTTPS/SSL).

Table 4. Incoming vSnap firewall connections				
Port	Protocol	Firewall	Service	Description
22	TCP	Accept	SSH	Used for troubleshooting vSnap servers

Port	Protocol	Firewall	Service	Description
111	TCP	Accept	RPC Port Bind	Allows clients to discover ports that Open Network Connectivity (ONC) clients require to communicate with ONC servers (internal)
137	UDP	Accept	SMB/CIFS	Used for SMB or CIFS data transfer to and from vSnap servers (internal)
138	UDP	Accept	SMB/CIFS	Used for SMB or CIFS data transfer to and from vSnap servers (internal)
139	ТСР	Accept	SMB/CIFS	Used for SMB or CIFS data transfer to and from vSnap servers (internal)
445	ТСР	Accept	SMB/CIFS	Used for SMB or CIFS data transfer to and from vSnap servers (internal)
2049	ТСР	Accept	NFS	Used for NFS data transfer to and from vSnap servers (internal)
3260	TCP	Accept	iSCSI	Used for iSCSI data transfer to and from vSnap servers (internal)
8900	TCP	Accept	HTTPS	vSnap server REST APIs
20048	ТСР	Accept	NFS	Used for NFS data transfer to and from vSnap servers (internal)

# **VADP** proxy requirements

In IBM Spectrum Protect Plus, running virtual machine backup jobs through VADP can be taxing on system resources. By creating VADP backup job proxies, you enable load sharing and load balancing for your IBM Spectrum Protect Plus backup jobs. If proxies exist, the entire processing load is shifted from the IBM Spectrum Protect Plus appliance onto the proxies.

This feature has been tested only for SUSE Linux Enterprise Server and Red Hat environments. The feature supported only in 64-bit quad core or higher configurations with a minimum kernel of 2.6.32.

VADP proxies support the following VMware transport modes: File, SAN, HotAdd, NBDSSL, and NBD. For more information about VMware transport modes, see Virtual Disk Transport Methods.

This feature is supported only in 64-bit quad core or higher configurations in the following Linux environments:

- CentOS Linux 6.5 and later maintenance and modification levels (beginning with 10.1.1 patch 1)
- CentOS Linux 7.0 and later maintenance and modification levels (beginning with 10.1.1 patch 1)
- Red Hat Enterprise Linux 6, Fix pack 4 and later maintenance and modification levels
- Red Hat Enterprise Linux 7 and later maintenance and modification levels
- SUSE Linux Enterprise Server 12 and later maintenance and modification levels

For more information and sizing guidance, see the IBM Spectrum Protect Plus Blueprints.

For initial deployment of a VADP proxy server, ensure that your Linux machine meets the following minimum requirements:

- 64-bit quad core processor
- 8 GB RAM required, 16 GB preferred
- 60 GB free disk space

The increase of used CPUs and concurrency on the VADP proxy server requires the memory that is allocated on the proxy server to be increased accordingly.

The proxy must be able to mount NFS file systems, which in many cases requires an NFS client package to be installed. The exact package details vary based on the distribution.

Each proxy must have a fully qualified domain name and must be able to resolve and reach the vCenter. vSnap servers must be reachable from the proxy. Port 8098 on the VADP proxy server must be open when the proxy server firewall is enabled.

# **VADP** proxy ports

The following ports are used by VADP proxies. Ports that are indicated with "Accept" in the Firewall Rule column use secure connections (HTTPS or SSL).

Table 5. Incoming VADP proxy firewall connections				
Port	Protocol	Firewall	Service	Description
22	TCP	Accept	SSH	Port 22 is used to push the VADP proxy to the host node.
8098	TCP	Accept	VADP	Default port for TLS-based REST API communications between the IBM Spectrum Protect Plus server and the VADP proxy.

Table 6. Outgoing VADP proxy firewall connections			
Port	Protocol	Service	Description
111	ТСР	vSnap RPC Port Bind	Allows clients to discover ports that ONC clients require to communicate with ONC servers (internal).
443	ТСР	VMware ESXi Host/ vCenter	Client connections to vCenter.
902	TCP	VMware ESXi Host	Network File Copy (NFC0 provides a file- type-aware FTP service for vSphere components. ESXi uses NFC for operations such as copying and moving data between datastores by default.
2049	ТСР	vSnap NFS	Used for NFS file sharing by using the vSnap server.
5671	ТСР	RabbitMQ	Message framework used to manage messages that are produced and consumed by the VADP proxy and VMware job management workers. Also facilitates the job log.
8761	ТСР	Discovery Server	Automatically discovers VADP proxies and is used by IBM Spectrum Protect Plus VM backup operations.
20048	TCP	vSnap mount	Mounts vSnap file systems on clients such as the VADP proxy, application servers, and virtualization data stores.

Tip: VADP proxies can be pushed and installed on Linux-based servers over SSH port 22.

If the firewall command script is not available on your system, edit the firewall manually to add necessary ports, and restart the firewall. More information on editing firewall rules can be found here, <u>"Editing</u> firewall ports" on page 47.

# VADP proxy on vSnap server requirements

VADP proxies can be installed on vSnap servers in your IBM Spectrum Protect Plus environment. A combination VADP proxy and vSnap server must meet the minimum requirements of both devices.

Consult the system requirements of both devices and add the core and RAM requirements together to identify the minimum requirements of the combination VADP proxy and vSnap server.

Ensure that your combination VADP proxy and vSnap server meets the following recommended minimum requirements, which is the sum of the requirements for each device.

VADP proxy installed on a virtual vSnap server:

- 64-bit 8-core processor
- 48 GB RAM

All required VADP proxy and vSnap server ports must be open on the combination VADP proxy and vSnap server. Review the VADP proxy and vSnap ports sections of the system requirements for more information.

# **Cloud requirements**

To offload data to cloud storage, ensure that your IBM Spectrum Protect Plus and cloud environments meet the following requirements.

### Disk cache area

For all functionality relating to offload or restore from the cloud, the vSnap server requires a disk cache area on the vSnap server.

- During offload operations, this cache is used as a temporary staging area for objects that are pending upload to the cloud endpoint.
- During restore operations, the disk cache area is used to cache downloaded objects as well as to store any temporary data that might be written into the restore volume.

For instructions on sizing and installing the cache, see <u>Cloud offload configuration</u> or the <u>IBM Spectrum</u> Protect Plus Blueprints.

# **Certificate requirements**

- **Self-signed certificates:** If the cloud endpoint or repository server uses a self-signed certificate, the certificate must be specified (in Privacy Enhanced Mail (PEM) format) when registering the cloud or repository server in the IBM Spectrum Protect Plus user interface.
- Certificates signed by private Certificate Authority: If the cloud endpoint or repository server uses a certificate signed by a private Certificate Authority (CA), the endpoint certificate must be specified (in PEM format) when you register the cloud or repository server in the IBM Spectrum Protect Plus user interface. In addition, the root/intermediate certificate of the private CA must be added to the system certificate store in each vSnap server using the following procedure:
  - 1. Log in to the vSnap server console as the serveradmin user and upload any private CA certificates (in PEM format) to a temporary location.
  - 2. Copy each certificate file to the system certificate store directory (/etc/pki/ca trust/source/anchors/) by running the following command:

```
$ sudo cp /tmp/private-ca-cert.pem /etc/pki/ca-trust/source/anchors/
```

3. To incorporate the newly added custom certificate and update the system certificate bundle, run the following command:

```
$ sudo update-ca-trust
```

• Certificates signed by public Certificate Authority: If the cloud endpoint uses a public CA-signed certificate, no special action is needed. The vSnap server validates the certificate by using the default system certificate store.

# **Network requirements**

The following ports are used for communication between vSnap servers and cloud or repository server endpoints.

Table 7. Outgoing vSnap server firewall connections			
Port	Protocol	Service	Description
443	TCP	HTTPS	Allows vSnap to communicate with Amazon S3, Azure, or IBM Cloud Object Storage endpoints.
9000	TCP	HTTPS	Allows vSnap to communicate with IBM Spectrum Protect (repository server) endpoints.

Any firewalls or network proxies that run SSL Interception or Deep Packet Inspection for traffic between vSnap servers and cloud endpoints might interfere with SSL certificate validation on the vSnap servers. This interference can also cause cloud offload job failures. To prevent this interference, the vSnap servers must be exempted from SSL interception and inspection in the firewall or proxy configuration.

# **Cloud provider requirements**

Native lifecycle management is not supported. IBM Spectrum Protect Plus manages the lifecycle of uploaded objects automatically using an incremental-forever approach where older objects can still be used by newer snapshots. Automatic or manual expiration of objects outside of IBM Spectrum Protect Plus will lead to data corruption.

If the cloud provider uses an SSL certificate that is self-signed or signed by a private Certificate Authority, see Certificate requirements.

# **Amazon S3 cloud requirements**

- **Offload:** When the cloud provider is registered in IBM Spectrum Protect Plus, an existing bucket in one of the supported storage tiers must be specified: S3 Standard, S3 Intelligent-Tiering, S3 Standard-Infrequent Access, or S3 One Zone-Infrequent Access.
- Archive: When the cloud provider is registered in IBM Spectrum Protect Plus, an existing bucket in one of the supported storage tiers must be specified: S3 Standard, S3 Intelligent-Tiering, S3 Standard-Infrequent Access, or S3 One Zone-Infrequent Access. IBM Spectrum Protect Plus will directly upload data files to the Glacier tier. Some small metadata files will be stored in the default tier for the bucket. A copy of these metadata files is also placed into the Glacier tier for disaster recovery purposes.

# **IBM Cloud Object Storage requirements**

- Offload: When the cloud provider is registered in IBM Spectrum Protect Plus, an existing bucket must be specified. If the specified bucket has a WORM policy that locks objects for a certain time period, IBM Spectrum Protect Plus automatically detects the configuration and deletes snapshots after the WORM policy removes the lock.
- Archive: When the cloud provider is registered in IBM Spectrum Protect Plus, an existing bucket
  must be specified. If the specified bucket has a WORM policy that locks objects for a certain time
  period, IBM Spectrum Protect Plus automatically detects the configuration and deletes snapshots
  after the WORM policy removes the lock. IBM Spectrum Protect Plus creates a single lifecycle
  management rule on the bucket to migrate data files to the archive tier.

# **Microsoft Azure requirements**

- **Offload:** When the cloud provider is registered in IBM Spectrum Protect Plus, an existing container in a hot or cool storage account must be specified.
- **Archive:** When the cloud provider is registered in IBM Spectrum Protect Plus, an existing container in a hot or cool storage account must be specified. IBM Spectrum Protect Plus moves files between tiers on demand. Data files will be immediately moved to the archive tier and temporarily returned

to the hot tier only during a restore operation. Some small metadata files will be stored in the default tier for the container. A copy of these metadata files is also placed in the archive tier for disaster recovery purposes.

# **IBM Spectrum Protect (repository server) requirements**

- **Offload:** When the cloud provider is registered in IBM Spectrum Protect Plus, you cannot use an existing bucket. IBM Spectrum Protect Plus creates a uniquely named bucket for its own use.
- Archive: When the cloud provider is registered in IBM Spectrum Protect Plus, you cannot use an existing bucket. IBM Spectrum Protect Plus creates a uniquely named bucket for its own use. IBM Spectrum Protect Plus will directly upload data files to IBM Spectrum Protect tape storage. Some small metadata files will be stored in IBM Spectrum Protect object storage. A copy of these metadata files is also placed on IBM Spectrum Protect tape storage for disaster recovery purposes.

Table 8. Offload and archive requirements for cloud providers			
Operation	Provider	Requirements	
Offload	Amazon S3	An existing bucket must be specified from one of the supported storage tiers.	
Offload	IBM Cloud Storage	An existing bucket must be specified.	
Offload	Microsoft Azure	An existing container must be specified from the hot or cool storage tier.	
Offload	IBM Spectrum Protect	IBM Spectrum Protect Plus creates its own unique bucket.	
Archive	Amazon S3	Allows vSnap to communicate with IBM Spectrum Protect (repository server) endpoints.	
Archive	IBM Cloud Storage	An existing bucket must be specified from the archive tier.	
Archive	Microsoft Azure	An existing container must be specified from the hot storage tier and archive tier.	
Archive	IBM Spectrum Protect	IBM Spectrum Protect Plus creates its own unique bucket to be copied to IBM Spectrum Protect tape storage.	

For quick-start information to help you to set up and offload data to specific cloud providers, see: <u>Data</u> offload to cloud object storage with IBM Spectrum Protect Plus .

# **Hypervisor requirements**

Review the hypervisor requirements for IBM Spectrum Protect Plus.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

# **Hyper-V requirements**

The Microsoft Hyper-V server must meet the following minimum requirements:

Hyper-V Server 2016 or Microsoft Hyper-V on Windows Server 2016

Microsoft Hyper-V on Windows Server 2019

Backup and restore of shared virtual hard disks (shared VHDX) is not supported. For known issues and limitations, see https://www.ibm.com/support/docview.wss?uid=ibm10884592.

IBM Spectrum Protect Plus does not protect environments in which Hyper-V Replica is enabled.

The Microsoft iSCSI Initiator Service must be running on all Hyper-V servers, including cluster nodes. In the **Services** window, set the startup type for the Microsoft iSCSI Initiator Service to **Automatic** so that the service is available when the Hyper-V server or cluster node starts.

The **DiskPart** automount parameter must be enabled on the Hyper-V server. For more information about enabling the automount parameter, see the Automount topic at the Microsoft website.

Hyper-V servers can be registered using a Domain Name System (DNS) name or IP address. DNS names must be resolvable by IBM Spectrum Protect Plus. If the Hyper-V server is part of a cluster, all nodes in the cluster must be resolvable via DNS. If DNS is not available, you must add the server to the /etc/hosts file on the IBM Spectrum Protect Plus appliance by using the command line. If more than one Hyper-V server is set up in a cluster environment, you must add all of the servers to the /etc/hosts file. When you are registering the cluster in IBM Spectrum Protect Plus, register the Failover Cluster Manager.

# **VMware requirements**

The following VMware vSphere versions are supported:

- vSphere 5.5, including all updates and patch levels
- vSphere 6.0, including all updates and patch levels
- vSphere 6.5, including all updates and patch levels
- vSphere 6.7, including all updates and patch levels

Ensure that latest version of VMware Tools is installed in your environment. IBM Spectrum Protect Plus was tested with VMware Tools 9.10.0 installed.

Physical RDM (pRDM) volumes do not support snapshots. Virtual machines that contain one or more raw device mapping (RDM) volumes that are provisioned in physical-compatibility mode (pRDM) are backed up. However, the pRDM volumes are not processed as part of the virtual machine backup operation.

# File indexing and restore requirements

Review file indexing and restore requirements for IBM Spectrum Protect Plus.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

iSCSI disks that are directly mapped to the guest operating system will not be indexed. Supported volumes include VMDK or VHD volumes that are mounted through the configuration of the associated virtual machine.

The amount of free space required for the metadata in the catalog depends on the total number of files in the environment. To catalog one million files, the catalog volume in the IBM Spectrum Protect Plus appliance requires roughly 350 MB of free space per retained version. The space used by file indexing metadata is reclaimed when the corresponding backup instances expire.

# **VMware requirements**

In the virtual machine settings under Advanced Configuration, the disk.enableUUID parameter must be present and set to true.

# Windows requirements

Supported operating systems	<ul> <li>Windows Server 2008 R2</li> <li>Windows Server 2012 R2 and Windows Server 2012 R2 core</li> <li>Windows Server 2016 and Windows Server 2016 Core</li> <li>Windows Server 2019 and Windows Server 2019 core</li> </ul>
Supported file systems	<ul><li>NTFS</li><li>ReFS</li><li>FAT</li></ul>
Supported disk storage types	Basic disks with  • MBR partitions  • GPT partitions  Restriction: The backup or restore of files on dynamic disks is not supported.

- IBM Spectrum Protect Plus supports only the operating systems available to your hypervisors. Review your hypervisor documentation for information about supported operating systems.
- File indexing and restore operations support SCSI disks in a Hyper-V environment. Integrated Drive Electronics (IDE) disks are not supported. Note that Generation 1 virtual machines require IDE boot disks; however, if additional SCSI disks are available, file indexing and restore operations will be supported on those disks.
- Windows Remote Shell (WinRM) must be enabled.

**Important:** IBM Spectrum Protect Plus can protect and restore virtual machines with other file systems, but only the previously listed file systems are eligible for file indexing and restore.

• When file indexing is performed in a Windows environment, the following directories on the resource are skipped:

```
\Program Files
\Program Files (x86)
\Windows
\winnt
```

**Note:** Files within these directories are not added to the IBM Spectrum Protect Plus inventory and are not available for file recovery.

• Ensure the latest version of VMware Tools is installed on VMware virtual machines, and Hyper-V Integration Services is installed on your Hyper-V virtual machines.

# **Space requirements**

- The C:\ drive must have sufficient temporary space to save the file indexing results.
- When file systems are indexed, temporary metadata files are generated under the /tmp directory and then deleted as soon as the indexing is complete. The amount of free space required for the metadata depends on the total number of files present on the system. Ensure that there is approximately 350 MB of free space per 1 million files.

# **Connectivity requirements**

• The hostname of the IBM Spectrum Protect Plus appliance should be resolvable from the Windows virtual machine. If the host name of the appliance is not resolvable, add the IP address of the

appliance in the hostAddress field in the IBM Spectrum Protect Plus configuration file, which can be found in the following location on the appliance:

/opt/virgo/repository/ecx-usr/deploy.vmware.vmdeployer.json

- The IP address of the virtual machine selected for indexing must be visible to the vSphere client or Hyper-V Manager.
- The Windows virtual machine selected for indexing must allow outgoing connections to port 22 (SSH) on the IBM Spectrum Protect Plus appliance.
- All firewalls must be configured to allow IBM Spectrum Protect Plus to connect to the server through WinRM.

# Authentication and privilege requirements

The credentials that are specified for the virtual machine must include a user with the following privileges:

The user identity must have the "Log on as a service" right, which is assigned through the
Administrative Tools control panel on the local machine (Local Security Policy > Local Policies >
User Rights Assignment > Log on as a service).

For more information about the "Log on as a service" right, see <u>Add the Log on as a service Right to</u> an Account.

- The default security policy uses the Windows NTLM protocol, and the user identity follows the default domain\Name format if the Hyper-V virtual machine is attached to a domain. The format <local administrator> is used if the user is a local administrator. Note that credentials must be established for the associated virtual machine through the **Guest OS Username** and **Guest OS Password** option within the associated backup job definition.
- The system login credential must have the permissions of the local administrator.

# **Kerberos requirements**

- Kerberos-based authentication can be enabled through a configuration file on the IBM Spectrum Protect Plus appliance. This setting will override the default Windows NTLM protocol. Note that Kerberos does not allow local user accounts to be used and is suitable only for environments in which all machines are on a single domain.
- For Kerberos-based authentication only, the user identity must be specified in the username@FQDN format. The specified user must be able to authenticate using the registered password to obtain a ticket-granting ticket (TGT) from the key distribution center (KDC) on the domain specified by the fully qualified domain name.
- Kerberos authentication also requires that the clock skew between the Domain Controller and the IBM Spectrum Protect Plus appliance is less than 5 minutes. Note that the default Windows NTLM protocol is not time dependent.

# **Group Policy Object requirements**

The Group Policy Object (GPO) setting for the Computer Configuration > Policies > Windows
Settings > Security Settings > Local Policies > Security Options > Network security: Restrict
NTLM: Incoming NTLM traffic, must be set to one of the following options:

- · Allow all
- · Allow all accounts

The Group Policy Object (GPO) setting for the Computer Configuration > Policies > Windows Settings > Security Settings > Local Policies > Security Options > Network security: Restrict NTLM: Outgoing NTLM traffic, must be set to one of the following options:

- · Allow all
- · Allow all accounts

### **Linux requirements**

Supported operating systems	Red Hat Enterprise Linux 6.4 and later maintenance and modification levels  CentOS 6.4 and later maintenance and modification levels
	Red Hat Enterprise Linux 7.0 and later maintenance and modification levels
	CentOS 7.0 and later maintenance and modification levels
	SUSE Linux Enterprise Server 12.0 and later maintenance and modification levels
Supported file systems	• ext2
	• ext3
	• ext4
	• XFS

• A file system created on a newer kernel version may not be mountable on a system with an older kernel, in which case restoring files from the newer to the older system is not supported.

IBM Spectrum Protect Plus supports only the operating systems available to your hypervisors. Review your hypervisor documentation for information about supported operating systems.

**Note:** IBM Spectrum Protect Plus can protect and restore virtual machines with other file systems, but only the previously listed file systems are eligible for file indexing and restore.

• When file indexing is performed in a Linux environment, the following directories on the resource are skipped:

```
/tmp
/usr/bin
/Drivers
/bin
/sbin
```

• Files in virtual file systems like /proc, /sys, and /dev are also skipped. Files within these directories are not added to the IBM Spectrum Protect Plus inventory and are not available for file recovery.

# **Space requirements**

- The system disk must have sufficient temporary space to save the file indexing results.
- When file systems are indexed, temporary metadata files are generated under the /tmp directory and then deleted when the indexing is complete. The amount of free space required for the metadata depends on the total number of files present on the system. Ensure that there is approximately 350 MB of free space available per 1 million files.

### **Software requirements**

- Python version 2.6 (any level) or 2.7 (any level) must be installed.
- Red Hat Enterprise Linux / CentOS 6.x only: Ensure the util-linux-ng package is up-to-date by running **yum update util-linux-ng**. Depending on your version or distribution, the package may be named util-linux.
- If data resides on LVM volumes, ensure the LVM version is 2.0.2.118 or later. Run **lvm version** to check the version and run **yum update lvm2** to update the package if necessary.
- If data resides on LVM volumes, the **lvm2-lvmetad** service must be disabled as it can interfere with the ability of IBM Spectrum Protect Plus to mount and re-signature volume group snapshots or clones. To disable the service, complete the following steps:

1. Run the following commands:

```
systemctl stop lvm2-lvmetad systemctl disable lvm2-lvmetad
```

2. Edit /etc/lvm/lvm.conf and specify the following setting:

```
use_lvmetad = 0
```

For details of the **lymetad** service, see The Metadata Daemon (lymetad).

If data resides on XFS file systems and the version of xfsprogs is between 3.2.0 and 4.1.9, the file
restore can fail due to a known issue in xfsprogs that causes corruption of a clone or snapshot file
system when its UUID is modified. To resolve this issue, update xfsprogs to version 4.2.0 or
above.

For more information, see Debian Bug report logs.

### **Connectivity requirements**

The SSH service must be running on port 22 on the server, and any firewalls must be configured to allow IBM Spectrum Protect Plus to connect to the server through SSH. The SFTP subsystem for SSH must also be enabled.

## Authentication and privilege requirements

The credentials specified for the virtual machine must specify a user that has the following **sudo** privileges:

- The sudoers configuration must allow the user to run commands without a password.
- The !requiretty setting must be set.

The recommended approach is to create a dedicated IBM Spectrum Protect Plus agent user with the following privileges. Sample configuration:

Create user: useradd -m sppagent
 where sppagent specifies the IBM Spectrum Protect Plus agent user.

• Set a password: passwd <sppagent>

Place the following lines at the end of your sudoers configuration file, typically /etc/sudoers. If your existing sudoers file is configured to import configurations from another directory (for example, /etc/sudoers.d), you can also place the lines in a new file in that directory:

```
Defaults: sppagent !requiretty sppagent ALL=(root) NOPASSWD:ALL
```

# **Microsoft Exchange Server requirements**

Before you install IBM Spectrum Protect Plus, review the hardware and software requirements for the product and other components.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

The Exchange database backup and restore requirements for IBM Spectrum Protect Plus are as follows.

# Configuration

Make sure that the Microsoft Exchange Server version that you are using is supported on your operating system.

# **Application Versions**

• Microsoft Exchange Server 2013 CU16 and later CU and maintenance levels: Standard or Enterprise editions.

- Microsoft Exchange Server 2016 CU 5 and later CU and maintenance levels: Standard and Enterprise editions.
- Microsoft Exchange Server 2019 and later maintenance levels: Standard and Enterprise editions.

Note: Microsoft Exchange database availability groups (DAG) are supported.

## **Operating Systems**

- Windows Server 2012R2 and later maintenance levels (64-bit kernel): Standard and Datacenter editions
- Windows Server 2016 and later maintenance levels (64-bit kernel): Standard and Datacenter editions
- Windows Server 2019 and later maintenance levels (64-bit kernel): Standard and Datacenter editions

**Note:** Windows Server 2019 Core installation is supported. However, the granular restore feature is not supported on a core installation.

### **Additional Notes**

Install the latest Microsoft Exchange Server patches and updates in your environment.

For information about virtualization support for Exchange Server, see the <u>"Prerequisites for Exchange Server"</u> on page 151.

## **Incremental backups**

IBM Spectrum Protect Plus uses update sequence number (USN) change journal technology to perform incremental backups in a Microsoft Exchange Server environment. The USN change journal provides write range tracking for a volume when the file size meets the minimum file size threshold requirement. The changed bytes offset and length extent information can be queried against a specific file.

To enable write range tracking, the system environment must meet the following requirements:

- Windows Server 2012 R2 or later
- New Technology File System (NTFS) Version 3.0 or later

The following technologies are not supported for changed bytes tracking:

- Resilient File System (ReFS)
- Server Message Block (SMB) 3.0 protocol
- SMB Transparent Failover (TFO)
- SMB 3.0 with scale-out file shares

By default, 512 MB of space is allocated for USN change journaling. In addition, when journal overflow is detected, the allocated space doubles in size when an overflow is detected, to a maximum of 2 GB.

The minimum space required for shadow copy storage is 100 MB, although more space might be required on systems with increased activity.

A base backup of a file is forced when the following conditions are detected:

- Journal discontinuity is reported. This can occur when the log reaches its maximum size, when journaling is disabled, or when the cataloged USN ID is changed.
- The file size is less than or equal to the tracking threshold size, which by default is 1 MB.
- A file is added after a previous backup job.

### **Software**

Ensure that a supported version of a Windows 64-bit operating system is installed.

The following prerequisites from Microsoft are required and must be installed prior to using IBM Spectrum Protect Plus:

• Windows PowerShell 4 or later

· Windows Management Framework 4 or later

When using Microsoft Exchange Server 2013 and the granular restore feature, the minimum level supported for Microsoft Exchange Messaging API (MAPI) Client and Collaboration Data Objects (MAPI/CDO) is version 6.5.8320.0.

**Note:** MAPI/CDO is required for Microsoft Exchange Server 2013 only. It is not required if you are running Microsoft Exchange Server 2016 or Exchange Server 2019.

When using the granular restore feature with Microsoft Exchange Server 2016 or Microsoft Exchange Server 2019, Microsoft 32-bit Outlook 2016 or Microsoft 32-bit Outlook 2019 is required.

The following prerequisites from Microsoft are required, and installed automatically by the IBM Spectrum Protect Plus granular restore feature, if not already present on your virtual machine.

- 32-bit Microsoft Visual C++ 2012 Redistributable Package
- 64-bit Microsoft Visual C++ 2012 Redistributable Package
- 32-bit Microsoft Visual C++ 2017 Redistributable Package
- 64-bit Microsoft Visual C++ 2017 Redistributable Package
- Microsoft .NET Framework 4.5
- Microsoft ReportViewer 2012 SP1 Redistributable
- Microsoft SQL Server 2012 System CLR Types
- Microsoft SQL Server 2014 System CLR Types
- Microsoft SQL Server 2016 System CLR Types

**Tip:** Installation of these prerequisites might require a system restart. To avoid a system restart, ensure that these prerequisites are installed before starting the IBM Spectrum Protect Plus granular restore feature.

# **Privileges**

IBM Spectrum Protect Plus agent users have the following privileges:

Microsoft Exchange Server is protected by role-based authentication. In order to get the Microsoft Exchange agent to work in your IBM Spectrum Protect Plus environment, you must set up the appropriate privileges. For more information, see "Privileges" on page 151.

### **Ports**

The following ports are used by IBM Spectrum Protect Plus agent users. Ports that are indicated with "Accept" in the Firewall Rule column use secure connections (HTTPS or SSL).

Table 9. Incoming IBM Spectrum Protect Plus agent firewall connections					
Port	Protocol	Firewall Rule	Service	Description	
5985	ТСР	Accept	WinRM	Windows Remote Management Service	
5986	ТСР	Accept	WinRM	Secure Windows Remote Management Service	

Table 10. Outgoing IBM Spectrum Protect Plus agent firewall connections				
Port	Protocol	Service	Description	
3260*	TCP	vSnap iSCSI	iSCSI vSnap target port used for mounting LUNS for backup and recovery	
137	UDP	vSnap SMB/CIFS	vSnap SMB or CIFS target port used for mounting filesystem shares for transaction log backup and recovery	
138	UDP	vSnap SMB/CIFS	vSnap SMB or CIFS target port used for mounting filesystem shares for transaction log backup and recovery	
139	ТСР	vSnap SMB/CIFS	vSnap SMB or CIFS target port used for mounting filesystem shares for transaction log backup and recovery	
445	ТСР	vSnap SMB/CIFS	vSnap SMB or CIFS target port used for mounting filesystem shares for transaction log backup and recovery	

<sup>\*</sup>iSCSI initiator is required on this node.

### **Hardware**

System	Disk Space	Disk Space for Granular Restore Operations
x64: Compatible hardware supported by the operating system and the Microsoft Exchange Server	A minimum of 200 MB of disk space for the product to be installed	At least 2.1 GB disk space for "Additional Microsoft prerequisites", which will be installed automatically if they are not already

# **Db2** requirements

Before you register Db2 with IBM Spectrum Protect Plus, ensure that your environment meets the outlined requirements.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

The IBM Db2 database backup and restore requirements for IBM Spectrum Protect Plus are as follows.

# **Configuration requirements**

The following IBM Db2 databases are supported:

- IBM Db2 Version 10.5 and later maintenance levels and modification levels: Enterprise Server Edition.
- IBM Db2 Version 11.1 and later maintenance levels and modification levels: Enterprise Server Edition.

### **Operating systems**

The following operating systems are supported:

- On PowerPC®:
  - AIX® 7.1 and later modification and fix pack levels (64-bit kernel).
  - AIX 7.2 and later modification and fix pack levels (64-bit kernel).
- On Linux x86 x64:
  - Red Hat Enterprise Linux 6.8 and later maintenance levels and modification levels.
  - Red Hat Enterprise Linux 7 and later maintenance levels and modification levels.
  - SUSE Linux Enterprise Server 11.0 SP4 and later maintenance levels and modification levels.
  - SUSE Linux Enterprise Server 12.0 SP1 and later maintenance levels and modification levels.
- On Linux on Power® System (little endian)
  - Red Hat Enterprise Linux 7.1 and later maintenance and modification levels.
  - SUSE Linux Enterprise Server 12.0 SP1 and later maintenance and modification levels.

### **Additional notes**

Install the latest IBM Db2 patches and updates in your environment.

IBM Db2 pureScale® is not supported

Ensure that your Db2 environment is configured to meet the following criteria:

- Db2 archive logging is activated and Db2 is in recoverable mode.
- Logical volumes holding Db2 table spaces (data and temporary table spaces), the local database directory, and Db2 log files are managed by Logical Volume Manager (LVM2) on Linux and by JFS2 on AIX respectively. LVM2 on Linux and JFS2 on AIX are used for creating temporary volume snapshots. The logical volume grows in size with data as it changes on the source volume while the snapshot exists. For more information, see "LVM2 and JFS2" on page 131.
- Db2 must be in parallel backup mode if multiple partitions are to be protected. Parallel backup mode can be enabled by using Db2 registry variables. For more information, see "Prerequisites for Db2" on page 129.

### **Software**

Review the following software requirements:

• The bash and sudo packages must be installed. Sudo must be version 1.7.6p2 or above. Run sudo -V to check the version.

**Note:** The required bash and sudo packages are included in the supported Linux86\_64 and Linux Power Systems (little endian) operating systems.

- Python version 2.6 (any level) or 2.7 (any level) must be installed on Linux.
- Python version 2.7.x must be installed on AIX.
- Ensure that the supported version of Linux x86\_64, Linux Power Systems (little endian), or AIX is installed.

### Connectivity

Ensure that the following connectivity criteria are in place:

- The SSH service is running on port 22 on the server.
- Firewalls must be configured to allow IBM Spectrum Protect Plus to connect to the server using SSH.
- The SFTP subsystem for SSH is enabled.

- The server can be registered by using a DNS name or IP address. DNS names must be resolvable by IBM Spectrum Protect Plus.
- On AIX, ensure that the NFS communication is configured with reserved ports by using the command: nfso -p -o nfs\_use\_reserved\_port=1.

## **Authentication and privileges**

The Db2 server must be registered in IBM Spectrum Protect Plus by using an operating system user that exists on the Db2 server (referred to as IBM Spectrum Protect Plus agent user).

Ensure that the password is correctly configured and that the user can log in without facing any other prompts, such as prompts to reset the password.

The IBM Spectrum Protect Plus agent user must have the following privileges:

- Privileges to run commands as the root user and as the Db2 software owner user by using sudo. IBM Spectrum Protect Plus requires this for various tasks such as discovering storage layouts, mounting and unmounting disks, and managing databases.
  - The sudoers configuration must allow the IBM Spectrum Protect Plus agent user to run commands without a password.
  - The !requiretty setting must be set.
- Privileges to read the Db2 inventory using /usr/local/bin/db21s. IBM Spectrum Protect Plus requires this privilege to discover and collect information about IBM Db2 instances and databases.

### **Ports**

The following ports are used by IBM Spectrum Protect Plus agents. Ports that are marked as Accept use a secure connection (HTTPS/SSL).

Table 11. Incoming IBM Spectrum Protect Plus agent firewall connections					
Port Protocol Firewall Service Description					
22	TCP	Accept	SSH	Used for SSH data transfer to and from the internal vSnap server.	

Table 12. Outgoing IBM Spectrum Protect Plus agent firewall connections				
Port	Protocol Service		Description	
111	TCP	vSnap RPC Port Bind	Allows clients to discover ports that Open Network Computing (ONC) clients require to communicate with ONC servers.	
2049	ТСР	vSnap NFS	Used for NFS file sharing via vSnap.	
20048	TCP	vSnap NFS Mount	Mounts vSnap file systems on clients such as the VADP proxy, application servers, and virtualization data stores.	

# **MongoDB requirements**

Before you register MongoDB with IBM Spectrum Protect Plus, ensure that your environment meets the outlined requirements.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

The MongoDB database backup and restore requirements for IBM Spectrum Protect Plus are as follows.

## **Configuration requirements**

The following MongoDB database versions are supported:

- MongoDB Version 3.6 and later maintenance levels and modification levels: Community Server and Enterprise Server Editions.
- MongoDB Version 4.0 and later maintenance levels and modification levels: Community Server and Enterprise Server Editions.

## **Operating systems**

The following operating systems are supported:

- On Linux x86\_x64:
  - Red Hat Enterprise Linux 6.8 and later maintenance levels and modification levels
  - CentOS 6.8 and later maintenance levels and modification levels
  - Red Hat Enterprise Linux 7 and later maintenance levels and modification levels
  - CentOS 7 and later maintenance levels and modification levels
  - SUSE Linux Enterprise Server 12.0 SP1 and later maintenance levels and modification levels
- On Linux Power Systems (little endian):
  - Red Hat Enterprise Linux 7.1 and later maintenance and modification levels
  - CentOS 7 and later maintenance and modification levels

**Note:** On Linux Power Systems (little endian), only MongoDB enterprise server edition is supported.

### **Additional notes**

To help optimize performance, install the latest MongoDB patches and updates available for your environment.

Ensure that your MongoDB environment is configured to meet the following criteria:

- MongoDB is configured as a standalone instance or replica set. Backup operations of MongoDB sharded cluster instances are not supported. A backup always includes all databases in the instance.
- The MongoDB instance is configured to use the WiredTiger Storage Engine.
- The user in the MongoDB application server registration in IBM Spectrum Protect Plus must be able to retrieve server information and status from the MongoDB admin database.
- Logical volumes of MongoDB data and log paths are managed by Linux Logical Volume Manager (LVM2). LVM2 is used for creating temporary volume snapshots. The database files and the journal must be located on a single volume. The logical volume grows in size with data as it changes on the source volume while the snapshot exists. For more information, see "Linux LVM2" on page 184.

### **Software**

Review the following software requirements:

• Python version V2.6 (any level) or V2.7 (any level) must be installed.

- When the MongoDB application server runs RHEL 6 or CentOS 6, ensure that the openss1 package is at version 1.0.1e-57 or above. Run "yum update openss1" to update to this requirement.
- Ensure that the supported version of Linux x86\_64 or Linux Power Little Endian is installed.

### Connectivity

Ensure that the following connectivity criteria are in place:

- SSH service is running on port 22 on the server.
- Firewalls must be configured to allow IBM Spectrum Protect Plus to connect to the server using SSH.
- The SFTP subsystem for SSH is enabled.
- The application server can be registered in IBM Spectrum Protect Plus by using a DNS name or an IP address. DNS names must be resolvable by IBM Spectrum Protect Plus.

## **Authentication and privileges**

The MongoDB server must be registered in IBM Spectrum Protect Plus using an operating system user that exists on the MongoDB server (referred to as *IBM Spectrum Protect Plus agent user* for the rest of this topic).

Ensure that the password is correctly configured and that the user can log in without facing any other prompts, such as prompts to reset the password.

On MongoDB, SSL-based encryption and certificate-based authentication is not supported.

On MongoDB Enterprise Server Editions, only on-storage encryption is supported.

The IBM Spectrum Protect Plus agent user must have the following privileges:

- Privileges to run commands as the root user and as the MongoDB software owner user by using sudo. IBM Spectrum Protect Plus requires this privilege for tasks such as discovering storage layouts, mounting and unmounting disks, and managing databases.
  - The sudoers configuration must allow the IBM Spectrum Protect Plus agent user to run commands without a password.
  - The !requiretty setting must be set.
- Privileges to run the standard MongoDB server module /usr/local/bin/mongodb. IBM Spectrum Protect Plus requires this privilege to use the pymongo API to connect to the MongoDB servers by using the instance's assigned DNS/IP name and port. This mechanism is used to gather information about MongoDB instances and databases.
- If the MongoDB server is protected by role-based authentication, to get the MongoDB agent to work in your IBM Spectrum Protect Plus environment, you must set up the appropriate privileges. For more information, see Chapter 13, "Managing user access," on page 275.

### **Ports**

The following ports are used by IBM Spectrum Protect Plus agent users. Ports that are indicated with Accept in the Firewall Rule column use secure connections (HTTPS/SSL).

Table 13. Incoming IBM Spectrum Protect Plus agent firewall connections					
Port Protocol Firewall Rule Service Descript					
22	ТСР	Accept	SSH	Used for SSH data transfer to and from the internal vSnap server	

Table 14. Outgoing IBM Spectrum Protect Plus agent firewall connections				
Port	t Protocol Service		Description	
111	ТСР	vSnap RPC Port Bind	Allows clients to discover ports that Open Network Computing (ONC) clients require to communicate with ONC servers	
2049	TCP	vSnap NFS	Used for NFS file sharing via vSnap	
20048	TCP	vSnap NFS Mount	Mounts vSnap file systems on clients such as the VADP proxy, application servers, and virtualization data stores	

# **Oracle requirements**

Review the Oracle database backup and restore requirements for IBM Spectrum Protect Plus.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

## **Configuration requirements**

### **Database versions**

- Oracle 11g R2
- Oracle 12c R1
- Oracle 12c R2
- Oracle 18c

**Note:** For multi tenant databases in Oracle 12c and later, IBM Spectrum Protect Plus supports protection and recovery of the container database, including all pluggable databases (PDBs) under it. Granular recovery of specific PDBs can be performed via Instant Disk Restore recovery combined with RMAN.

## **Operating systems**

- AIX 6.1 TL9 and later maintenance and modification levels
- AIX 7.1 and later maintenance and modification levels
- Red Hat Enterprise Linux / CentOS 6.5 and later maintenance and modification levels
- Red Hat Enterprise Linux / CentOS 7.0 and later maintenance and modification levels
- SUSE Linux Enterprise Server 11.0 SP4 and later maintenance and modification levels
- SUSE Linux Enterprise Server 12.0 SP1 and later maintenance and modification levels
- SUSE Linux Enterprise Server 15.0 and later maintenance and modification levels

### **Additional notes**

- Oracle DataGuard is not supported.
- Databases must be in ARCHIVELOG mode. IBM Spectrum Protect Plus cannot protect databases running in NOARCHIVELOG mode.
- Real Application Cluster (RAC) database recoveries are not server pool-aware. IBM Spectrum Protect Plus can recover databases to a RAC, but not to specific server pools.

- RAC databases must be configured such that the RMAN Snapshot Control File location points to shared storage that is accessible to all cluster instances.
- When restoring an Oracle database that was configured for multi-threading at the time of backup, the restored database is non-multithreaded. The restored database must be manually reconfigured to use multi-threading.

### **Software**

- The bash and sudo packages must be installed. sudo must be version 1.7.6p2 or above. Run sudo -V to check the version.
- Python version 2.6.x or 2.7.x must be installed.
- RHEL/CentOS 6.x only:

Ensure the util-linux-ng package is up-to-date by running: **yum update util-linux-ng**. Depending on your version or distribution, the package may be named util-linux.

### Connectivity

- The SSH service must be running on port 22 on the server and any firewalls must be configured to allow IBM Spectrum Protect Plus to connect to the server by using SSH. The SFTP subsystem for SSH must also be enabled.
- The server can be registered using a DNS name or IP address. DNS names must be resolvable by IBM Spectrum Protect Plus.
- If DNS is not available, you must add the server to the /etc/hosts file on the IBM Spectrum Protect Plus appliance by using the command line.
- When registering Oracle RAC nodes, register each node using its physical IP or name. Do not use a virtual name or Single Client Access Name (SCAN).

## **Authentication and privileges**

- The Oracle server must be registered in IBM Spectrum Protect Plus using an operating system user that exists on the Oracle server. Hereafter, the user is referred to as the IBM Spectrum Protect Plus agent user.
- Ensure that the password is correctly configured and that the user can log in without other prompts, such as prompts to reset the password.

The IBM Spectrum Protect Plus agent user must have the following privileges:

- Privileges to run commands as root and as Oracle software owner users (for example, oracle, grid) using **sudo**. These privileges are required for tasks such as discovering storage layouts, mounting and unmounting disks, and managing databases and ASM.
  - The sudoers configuration must allow the IBM Spectrum Protect Plus agent user to run commands without a password.
  - The !requiretty setting must be set.
  - The ENV\_KEEP setting must allow the ORACLE\_HOME and ORACLE\_SID environment variables to be retained.
- Privileges to read the Oracle inventory. These privileges are required for tasks such as discovering and collecting information about Oracle homes and databases.

To achieve this, the IBM Spectrum Protect Plus agent user must belong to the Oracle inventory group, typically named oinstall.

For information about creating a new user with necessary privileges, see <u>"Sample configuration of an IBM"</u> Spectrum Protect Plus agent user" on page 36

#### NFS

The Oracle server must have the native Linux or AIX NFS client installed. IBM Spectrum Protect Plus uses NFS to mount storage volumes for backup and restore operations.

During database restore, the Oracle Direct NFS feature is required. IBM Spectrum Protect Plus automatically enables Direct NFS if it is not already enabled.

For Direct NFS to work correctly, the executable <0RACLE\_HOME>/bin/oradism under each Oracle home must be owned by root and have setuid privileges. This is typically pre-configured by the Oracle installer, but on certain systems, the binary might not have the required privileges. For more information, see the document Database Startup Failed with Direct NFS on the Oracle support website.

Run the following commands to set the correct privileges:

- chown root:oinstall <ORACLE\_HOME>/bin/oradism
- chmod 750 <ORACLE\_HOME>/bin/oradism

where oinstall specifies the group that owns the installation.

## **Database discovery**

IBM Spectrum Protect Plus discovers Oracle installations and databases by looking through the files /etc/oraInst.loc and /etc/oratab, as well as the list of running Oracle processes. If the files are not present in their default location, the "locate" utility must be installed on the system so that IBM Spectrum Protect Plus can search for the files.

IBM Spectrum Protect Plus discovers databases and their storage layouts by connecting to running instances and querying the locations of their datafiles, log files, and so on. In order for IBM Spectrum Protect Plus to correctly discover databases during cataloging and copy operations, databases must be in "MOUNTED," "READ ONLY," or "READ WRITE" mode. IBM Spectrum Protect Plus cannot discover or protect database instances that are shut down.

### **Block change tracking**

IBM Spectrum Protect Plus requires Oracle Block Change Tracking to be enabled on protected databases in order to efficiently perform incremental backups. If Block Change Tracking is not already enabled, IBM Spectrum Protect Plus enables it automatically during the backup job.

To customize the placement of the Block Change Tracking file, you must manually enable the Block Change Tracking feature before running an associated backup job. If the feature is enabled automatically by IBM Spectrum Protect Plus, the following rules are used to determine the placement of the Block Change Tracking file:

- If the **db\_create\_file\_dest** parameter is set, the Block Change Tracking file is created in the location specified by this parameter.
- If the **db\_create\_file\_dest** parameter is not set, the Block Change Tracking file is created in the same directory as the SYSTEM tablespace.

# Log backup

- The **cron** daemon must be enabled on the application server.
- The IBM Spectrum Protect Plus agent user must have the necessary privileges to use the **crontab** command and create cron jobs. Privileges can be granted through the cron.allow configuration file.

## Sample configuration of an IBM Spectrum Protect Plus agent user

The commands below are examples for creating and configuring an operating system user that IBM Spectrum Protect Plus will use to log in to the Oracle server. The command syntax may vary depending on your operating system type and version.

Create the user that will be designated as the IBM Spectrum Protect Plus agent user:useradd -m sppagent

- Set a password: passwd sppagent
- If using key-based authentication, place the public key in the /home/sppagent/.ssh/ authorized\_keys directory, or the appropriate file depending on your SSHD configuration, and ensure that the correct ownership and permissions are set, such as:

```
chown -R sppagent:sppagent/home/sppagent/.ssh
chmod 700 /home/sppagent/.ssh
chmod 600 /home/sppagent/.ssh/authorized_keys
```

- Add the user to the Oracle installation and OSDBA group: usermod -a -G oinstall, dba sppagent
- If ASM is in use, also add the user to the OSASM group: usermod -a -G asmadmin sppagent
- Place the following lines at the end of your sudoers configuration file, typically /etc/sudoers. If your existing sudoers file is configured to import configuration from another directory (for example, /etc/sudoers.d), you can also place the lines in a new file in that directory:

```
Defaults:sppagent !requiretty
Defaults:sppagent env_keep+="ORACLE_HOME"
Defaults:sppagent env_keep+="ORACLE_SID"
sppagent ALL=(ALL) NOPASSWD:ALL
```

### **Ports**

The following ports are used by IBM Spectrum Protect Plus agent users. Ports that are indicated with "Accept" in the Firewall Rule column use a secure connection (HTTPS or SSL).

Table 15. Incoming IBM Spectrum Protect Plus agent firewall connections					
Port	Protocol	Firewall Rule	Service	Description	
22	ТСР	Accept	SSH	Used for SSH data transfer to and from the internal vSnap server.	

Table 16. Outgoing IBM Spectrum Protect Plus agent firewall connections				
Port	Protocol	col Service		
111	TCP	vSnap RPC Port Bind	Allows clients to discover ports that Open Network Computing (ONC) clients require to communicate with ONC servers.	
443	TCP	HTTPS	Allows the Oracle server to communicate with IBM Spectrum Protect Plus for sending alerts in case of log backup failures.	
2049	TCP	vSnap NFS	Used for NFS file sharing via vSnap.	

Table 16. Outgoing IBM Spectrum Protect Plus agent firewall connections (continued)					
Port	Description				
20048	TCP	vSnap NFS Mount	Mounts vSnap file systems on clients such as the VADP Proxy, application servers, and virtualization data stores.		

# **Microsoft SQL Server requirements**

Review the Microsoft SQL Server database backup and restore requirements for IBM Spectrum Protect Plus.

To help ensure that backup and restore operations can be run successfully, your system must meet the hardware and software requirements. Use the following requirements as a starting point. For the most current requirements, which might include updates, see technote 2013790.

# Configuration

## **Database versions**

- SQL Server 2008 R2 SP3
- SOL Server 2012
- SQL Server 2012 SP2
- SQL Server 2014
- SQL Server 2016
- SQL Server 2017

For the best performance, install the latest SQL Server patches and updates in your environment.

## **Operating systems**

- Windows Server 2012 R2
- Windows Server 2016
- Windows Server 2019

Windows Remote Shell (WinRM) must be enabled.

An iSCSI route must be enabled between the SQL Server system and vSnap server. For more information, see Microsoft iSCSI Initiator Step-by-Step Guide.

IBM Spectrum Protect Plus inventory jobs discover system databases and mark the databases that are eligible for protection. Log backups are marked as ineligible for all system databases and databases running in simple recovery model.

### **In-Memory OLTP**

In-Memory online transaction processing (OLTP) is a memory-optimized database engine that is used to improve database application performance. This engine is supported in SQL Server 2014 and later. The following requirements and limitations apply to In-Memory OLTP usage:

- The maximum restore file path must have fewer than 256 characters. If the original path exceeds this length, consider using a customized restore file path to reduce the length.
- The metadata that can be restored is subject to Volume Shadow Copy Service (VSS) and SQL Server restore capabilities.

### **Incremental backup**

IBM Spectrum Protect Plus uses update sequence number (USN) change journal technology to perform incremental backups in an SQL Server environment. The USN change journal provides write range tracking for a volume when the file size meets the minimum file size threshold requirement. The changed bytes offset and length extent information can be queried against a specific file.

The following requirements enable write range tracking:

- Windows Server 2012 R2 or later
- · NTFS version 3.0 or later

The following technologies are not supported for changed bytes tracking:

- Resilient File System (ReFS)
- Server Message Block (SMB) 3.0 protocol
- SMB TFO (Transparent Failover)
- SMB 3.0 with Scale-out file shares (SO)

By default, 512 MB of space is allocated for USN change journaling. In addition, when journal overflow is detected, a 2 GB journal size is allocated to manage the busy file system.

The minimum space required for shadow copy storage is 100 MB, although more space might be required on systems with increased activity. The SQL Server agent checks the source volume space and will cause a backup to fail if the free space on the source volume is less than 100 MB. A warning message is displayed in the job log when free space is less than 10%, and then the backup proceeds.

A base backup is forced when the following conditions are detected:

- Journal discontinuity is reported due to the log reaching the maximum size, disabling of the journaling, or changing of the cataloged USN ID.
- The file size is less than or equal to the tracked threshold size, which by default is 1MB.
- A file is added after a previous backup job.

### Log backup

Prior to copying log files to the vSnap repository, IBM Spectrum Protect Plus uses the backup folder that is configured for the SQL server instance to stage the collection of logs. Sufficient free space must be available to store transaction logs between backup jobs. The staging area can be modified by changing the backup folder configuration by using SQL Server Management Studio (SSMS).

To ensure that SQL Server Log Backup works properly, a Windows Group Policy change might be required.

The Group Policy Object (GPO) setting for the **Network security: LAN Manager authentication level** policy, located at **Computer Configuration > Windows Settings > Security Settings > Local Policies > Security Options**, must be set to one of the following options:

- Not Defined
- Send NTLMv2 response only
- Send NTLMv2 response only. Refuse LM
- Send NTLMv2 response only. Refuse LM & NTLM

The **Send NTLM response only** option is not compatible with the vSnap CIFS or SMB version and can cause CIFS authentication problems.

The Group Policy Object (GPO) setting for the Computer Configuration > Policies > Windows Settings > Security Settings > Local Policies > Security Options > Network security: Restrict NTLM: Incoming NTLM traffic, must be set to one of the following options:

- · Allow all
- · Allow all accounts

The Group Policy Object (GPO) setting for the Computer Configuration > Policies > Windows Settings > Security Settings > Local Policies > Security Options > Network security: Restrict NTLM: Outgoing NTLM traffic, must be set to one of the following options:

- · Allow all
- Allow all accounts

## Configuring SQL Server AlwaysOn availability groups

Configure the preferred instance for backup operations by using SQL Server Management Studio. Complete the following steps:

- 1. Select the **Availability Group** node.
- 2. Select the availability group you that you want to configure, and then, select **Properties**.
- 3. In the Availability Group Properties dialog box, select Backup Preferences.

Select any option in the **Where should backups occur** pane. When secondary replica is preferred, and more than one secondary replica is available, the IBM Spectrum Protect Plus job executor will select the first secondary replica in the preferred list that is reported by the IBM Spectrum Protect Plus SQL Server agent.

The SQL Server agent sets the VSS backup type to COPY\_ONLY.

### **Registration and authentication**

Register each SQL server with IBM Spectrum Protect Plus by name or IP address. When registering a SQL Server Cluster (AlwaysOn) node, register each node by name or IP address. Note that the IP address must be reachable from the IBM Spectrum Protect Plus server and from the vSnap server. Both must have a Windows Remote Management (WinRM) service that is listening on port 5985. The fully qualified domain name must be resolvable and can be routed from the IBM Spectrum Protect Plus server and from the vSnap server.

The user identity must have sufficient rights to install and start the IBM Spectrum Protect Plus Tools Service on the node, including **Log on as a service** rights. For more information, see the article, <u>Add the Log on as a service</u> Right to an Account, at the Microsoft website.

The user identity follows the default *domain\Name* format if the virtual machine is attached to a domain. The format *local administrator* is used if the user is a local administrator.

# **Kerberos**

Kerberos-based authentication can be enabled by specifying a configuration file on the IBM Spectrum Protect Plus appliance. The settings will override the default Windows NTLM protocol.

For Kerberos-based authentication only, the user identity must be specified in the username@FQDN format. The user name must be able to authenticate by using the registered password to obtain a ticket-granting ticket (TGT) from the key distribution center (KDC) on the domain specified by the fully qualified domain name.

## **Privileges**

The IBM Spectrum Protect Plus agent user of an SQL server must have the following permissions:

- SQL Server public and sysadmin permissions
- Windows local administration permission, which are required by the VSS framework, and volume and disk access
- Permissions to access cluster resources in an SQL Server AlwaysOn and SQL Server FCI environment.

Every Microsoft SQL Server host can use a specific user account to access the resources of that particular SQL Server instance.

The SQL Server VDI-based framework is used to interact with SQL Server databases and to log backup and restore operations. A VDI connection requires SQL Server sysadmin permissions. The owner of a restored database is not changed to the original owner. A manual step is required to modify the owner of a restored database. For more information about the VDI framework, see the following Microsoft article: SQL Server VDI backup and restore operations require Sysadmin privileges.

The target SQL Server service account must have permissions to access SQL Server restore files. See "Administrative Considerations" in the following Microsoft article: Securing Data and Log Files .

The Windows Task Scheduler is used to schedule log backups. Depending on the environment, users may receive the following error: A specified logon session does not exist. It may already have been terminated. This error is due to a Network access Group Policy setting that needs to be disabled. For more information on how to disable this GPO, please see the following Microsoft Support article: A specified logon session does not exist. It may already have been terminated, error when you try to map to a network drive of a DFS share.

### **Ports**

The following ports are used by IBM Spectrum Protect Plus agent users. The ports that are indicated with "Accept" use a secure connection (HTTPS or SSL).

Table 17. Incoming IBM Spectrum Protect Plus agent firewall connections					
Port	Protocol	Firewall	Service	Description	
5985	ТСР	Accept	WinRM	Windows Remote Management Service	
5986	ТСР	Accept	WinRM	Secure Windows Remote Management Service	

Table 18. Outgoing IBM Spectrum Protect Plus agent firewall connections			
Port	Protocol	Service	Description
3260 iSCSI initiator is required on this node.	TCP	vSnap iSCSI	iSCSI vSnap target port used for mounting LUNS for backup and recovery operations.
137	UDP	vSnap SMB/CIFS	vSnap SMB/CIFS target port used for mounting filesystem shares for transaction log backup and recovery operations.
138	UDP	vSnap SMB/CIFS	vSnap SMB/CIFS target port used for mounting filesystem shares for transaction log backup and recovery operations.
139	TCP	vSnap SMB/CIFS	vSnap SMB/CIFS target port used for mounting filesystem shares for transaction log backup and recovery operations.

Table 18. Outgoing IBM Spectrum Protect Plus agent firewall connections (continued)			
Port	Protocol	Service	Description
443	TCP	HTTPS	Allows the SQL server to communicate with IBM Spectrum Protect Plus for sending alerts in case of log backup failures.
445	TCP	vSnap SMB/CIFS	vSnap SMB/CIFS target port used for mounting file system shares for transaction log backup and recovery operations.

# **Obtaining the IBM Spectrum Protect Plus installation package**

You can obtain the IBM Spectrum Protect Plus installation package from an IBM download site, such as Passport Advantage or Fix Central. These packages contain a files that are required to install or update the IBM Spectrum Protect Plus components.

## Before you begin

For the list of installation packages by component, and the links to the download site for the files, see technote 879861.

### **Procedure**

Download the appropriate installation file.

A different installation file is provided for installation on VMware and Microsoft Hyper-V systems. Ensure that you download the correct file for your environment.

**Important:** Do not change the names of the installation or update files. The original file names are required for the installation or update process to complete without errors.

### **Related concepts**

"Updating IBM Spectrum Protect Plus components" on page 81

You can update the IBM Spectrum Protect Plus virtual appliance, vSnap servers, and the VADP proxy servers to get the latest features and enhancements. Software patches and updates are installed by using the IBM Spectrum Protect Plus administrative console or command-line interface for these components.

### **Related tasks**

"Installing IBM Spectrum Protect Plus as a VMware virtual appliance" on page 43

To install IBM Spectrum Protect Plus in a VMware environment, deploy an Open Virtualization Format (OVF) template. Deploying an OVF template creates a virtual appliance containing the application on a VMware host such as an ESXi server.

"Installing IBM Spectrum Protect Plus as a Hyper-V virtual appliance" on page 44

To install IBM Spectrum Protect Plus in a Microsoft Hyper-V environment, import the IBM Spectrum Protect Plus for Hyper-V template. Importing a template creates a virtual appliance that contains the IBM Spectrum Protect Plus application on a Hyper-V virtual machine. A local vSnap server that is already named and registered is also installed on the virtual appliance.

"Installing vSnap servers" on page 51

When you deploy an IBM Spectrum Protect Plus appliance, a vSnap server is automatically installed. This server is the primary backup destination. In larger enterprise environments, additional vSnap servers might be required.

# Installing IBM Spectrum Protect Plus as a VMware virtual appliance

To install IBM Spectrum Protect Plus in a VMware environment, deploy an Open Virtualization Format (OVF) template. Deploying an OVF template creates a virtual appliance containing the application on a VMware host such as an ESXi server.

## Before you begin

Complete the following tasks:

- Review the IBM Spectrum Protect Plus system requirements in <u>"Component requirements"</u> on page 11 and <u>"Hypervisor requirements"</u> on page 21.
- Download the virtual appliance template installation file CC1QCML.ova from Passport Advantage<sup>®</sup>
   Online. For information about downloading files, see technote 879861.
- Verify the MD5 checksum of the downloaded template installation file. Ensure that the generated checksum matches the one provided in the MD5 Checksum file, which is part of the software download.
- During deployment, you will be prompted to enter network properties from the VMware user interface. You can enter a static IP address configuration, or leave all fields blank to use a DHCP configuration.
- To reassign a static IP address after deployment, you can use the NetworkManager Text User Interface (nmtui) tool. For more information, see "Assigning a static IP address" on page 46.

Note the following considerations:

- You might need to configure an IP address pool that is associated with the VM network where you plan to deploy IBM Spectrum Protect Plus. Correct configuration of the IP address pool includes the setup of IP address range (if used), netmask, gateway, DNS search string, and a DNS server IP address.
- If the hostname of the IBM Spectrum Protect Plus appliance changes after deployment, either through user intervention or if a new IP address is acquired through DNS, the IBM Spectrum Protect Plus appliance must be restarted.
- A default gateway must be configured properly before deployment. Multiple DNS strings are supported, and must be separated by commas without the use of spaces.
- For later versions of vSphere, the vSphere Web Client might be required to deploy IBM Spectrum Protect Plus appliances.
- IBM Spectrum Protect Plus has not been tested for IPv6 environments.

**Note:** The IBM Spectrum Protect Plus and vSnap appliance is a closed system and anti-virus (AV) installation is not supported on virtual or physical deployments.

#### **Procedure**

To install IBM Spectrum Protect Plus as a virtual appliance, complete the following steps:

- 1. Deploy IBM Spectrum Protect Plus by taking one of the following actions:
  - a) If you are using the vSphere Client, from the Actions menu, click Deploy OVF Template.
  - b) If you are using the vSphere Web Client, click **Create/Register VM**, then select **Deploy a virtual** machine from an OVF or OVA file.
- 2. Select an ESXi resource to run the virtual appliance. Click **Next**.
- 3. Review details. Click Next.

**Important:** If you are using the vSphere Web Client, verify that disk.enableUUID = true presents in **Extra Configuration**. If that is not the case or if you are using the vSphere Client, proceed with the installation steps and enable this option from the vSphere Web Client at a later time.

4. Specify the location of the CC1QCML. ova file and select it. Click Next.

- 5. Provide a meaningful name for the template, which becomes the name of your virtual machine. Identify an appropriate location to deploy the virtual machine. Click **Next**.
- 6. Select the storage to which the virtual appliance is to be installed. The datastore of this storage must be configured with the destination host. The virtual appliance configuration file and the virtual disk files will be stored in it. Ensure the storage is large enough to accommodate the virtual appliance including the virtual disk files associated with it. Select a disk format of the virtual disks. Thick provisioning allows for better performance of the virtual appliance. Thin provisioning uses less disk space at the expense of performance. Click **Next**.
- 7. Read the template details and accept the End User License Agreement. Check **I accept all license** agreements for vSphere Client or click **Accept** for vSphere Web Client. Click **Next**.
- 8. Select networks for the deployed template to use. Several available networks on the ESXi server might be available by clicking **Destination Network**. Select a destination network that allows you to define the appropriate IP address allocation for the virtual machine deployment. Click **Next**.
- 9. For vSphere Web Client, enter the property values for the virtual appliance: DNS, Default Gateway, Domain, Network IP Address and Network Prefix. A static IP address can be provided. If left blank, a dynamic IP address assigned by a DHCP server will be used. The network prefix must be entered using Classless Inter-Domain Routing (CIDR) notation where valid values are 1 24. Click **Next**.

**Note:** For vSphere Client, these properties can be configured using the NetworkManager Text User Interface (nmtui) tool. Additionally, information for the Search Domain field can be added using this command. For more information, see Assigning a static IP address.

- 10. Review your template settings. Click **Finish** to exit the wizard and to start deployment of the OVF template.
- 11. After the OVF template is deployed, power on your newly created VM. You can power on the VM from the vSphere Client.

Important: Wait several minutes for IBM Spectrum Protect Plus to initialize completely.

### What to do next

Once the virtual appliance has been deployed, the IBM Spectrum Protect Plus application as well as a local vSnap server which is built into it will be registered and installed on it automatically. To start IBM Spectrum Protect Plus, complete the following actions:

Action	How to
Connect to the console of the IBM Spectrum Protect Plus virtual appliance by using VMware Remote Console or SSH. Set up network configurations using the NetworkManager Text User Interface (nmtui).	See <u>Assigning a static IP address</u> .
Upload the product key.	See <u>"Uploading the product key" on page 47</u> .
Start IBM Spectrum Protect Plus from a supported web browser.	See "Start IBM Spectrum Protect Plus" on page 69.

# Installing IBM Spectrum Protect Plus as a Hyper-V virtual appliance

To install IBM Spectrum Protect Plus in a Microsoft Hyper-V environment, import the IBM Spectrum Protect Plus for Hyper-V template. Importing a template creates a virtual appliance that contains the IBM Spectrum Protect Plus application on a Hyper-V virtual machine. A local vSnap server that is already named and registered is also installed on the virtual appliance.

### Before you begin

Complete the following tasks:

- Review the IBM Spectrum Protect Plus system requirements in "Component requirements" on page 11 and "Hypervisor requirements" on page 21.
- Download the installation file CC1QDML.exe from Passport Advantage Online. For more information about downloading files, see technote 879861.
- Review Hyper-V system requirements. See System requirements for Hyper-V on Windows Server.
- Verify the MD5 checksum of the downloaded template installation file. Ensure that the generated checksum matches the one provided in the MD5 Checksum file, which is part of the software download.
- If the hostname of the IBM Spectrum Protect Plus virtual appliance changes after deployment, either through user intervention or if a new IP address is acquired through DNS, the IBM Spectrum Protect Plus virtual appliance must be restarted.
- All Hyper-V servers, including cluster nodes, must have the Microsoft iSCSI Initiator Service running in their Services lists. Set startup type of this service to Automatic so that it starts running when the server starts.
- Administrative privileges might be required to complete certain steps during the installation process.

**Note:** The IBM Spectrum Protect Plus and vSnap appliance is a closed system and anti-virus (AV) installation is not supported on virtual or physical deployments.

### **Procedure**

To install IBM Spectrum Protect Plus as a virtual appliance, complete the following steps:

- 1. Copy the CC1QDML. exe file to your Hyper-V server.
- 2. Open the installer and complete the Setup wizard.
- 3. Open Hyper-V Manager and select the required server.
- 4. From the **Actions** pane in Hyper-V Manager, click **Import Virtual Machine**. The Import Virtual Machine wizard opens. Click **Next**.
- 5. In the **Locate Folder** step, click **Browse** and go to the folder that was designated during the installation. Select the folder with **SPP-{release}** in it. Click **Next**.
- 6. In the **Select Virtual Machine** step, ensure the virtual machine **SPP-{release}** is selected and then click **Next**. The **Choose Import Type** window opens.
- 7. In the Choose Import Type step, select Register the virtual machine in-place (use the existing unique ID). Click Next.

**Important:** Do not import multiple IBM Spectrum Protect Plus virtual appliances on a single Hyper-V server.

- 8. In the Connect Network step, set the connection to the virtual switch to be used. Click Next.
- 9. In the **Summary** step, review the Description. Click **Finish** to close the Import Virtual Machine wizard.
- 10. In Hyper-V Manager, locate the new virtual machine named **SPP-{release}**. Right-click this virtual machine and click **Settings**.
- The settings for this virtual machine are displayed. In the left pane, click Hardware > IDE Controller
   Hard Drive.
- 12. In the Media section, ensure that the correct virtual hard disk is selected. Note the file name of the original virtual disk. Click **Edit**.
- 13. The Edit Virtual Hard Disk wizard opens. Go to the **Choose Action** step.
- 14. In the Choose Action step, click Convert and then click Next.
- 15. In the Choose Disk Format step, ensure that VHDX is selected. Click Next.
- 16. For the Choose Disk Type step, click Fixed Size. Click Next.
- 17. For the **Configure Disk** step, locate the folder to store the virtual disk file of the IBM Spectrum Protect Plus virtual appliance. Reuse the same file name that was noted in Step 12. If the same installation directory from Step 2 is reused, use a different name. Click **Next**.

**Important:** Ensure that the disk drive on which the folder is located has enough disk space available to accommodate the fixed-size virtual disk file.

- 18. In the **Summary** step, review the Description. Click **Finish** to close the Edit Virtual Hard Disk wizard and to initiate the conversion of the virtual disk. When the process completes, the original virtual hard disk file might be deleted.
- 19. In the settings window for the virtual machine, click **Browse**. Open the newly created virtual hard disk (VHDX) file that was created in the previous step.
- 20. Repeat steps 12-19 for each hard disk drive under **Hardware > SCSI Controller**. Click **OK** to close Settings.
- 21. In the Hyper-V Manager, right-click the virtual machine and click **Start**.
- 22. Use Hyper-V Manager to identify the IP address of the new virtual machine when the address is automatically assigned. To assign a static IP to the virtual machine, use the NetworkManager Text User Interface (nmtui) tool.

For more information, see "Assigning a static IP address" on page 46.

**Important:** IBM Spectrum Protect Plus or vSnap virtual machines that are deployed using Hyper-V failover clustering should be configured with a static media access control (MAC) address for each virtual network adapter. If a dynamic MAC address is used, the Linux networking configuration may be lost after failover because a new MAC address is assigned to the virtual network adapter. The MAC address may be configured by editing the settings of the virtual machine in the Hyper-V Manager or Failover Cluster Manage. Ensuring that each virtual network adapter is assigned a static MAC address will prevent the loss of the network configuration.

#### What to do next

After you install the virtual appliance, complete the following actions:

Action	How to
Restart the virtual appliance.	Refer to the documentation for the virtual appliance.
Upload the product key.	See <u>"Uploading the product key" on page 47</u> .
Start IBM Spectrum Protect Plus from a supported web browser.	See "Start IBM Spectrum Protect Plus" on page 69.

# **Assigning a static IP address**

To reassign a new static IP address after initial deployment, a network administrator can assign a static IP address by using the NetworkManager Text User Interface (nmtui) tool. Sudo privileges are required to run nmtui.

### **Procedure**

To reassign a new static IP address, ensure that the IBM Spectrum Protect Plus virtual machine is powered on and complete the following steps:

- 1. Log on to the virtual machine console with the user ID **serveradmin**. The initial password is sppDP758.
- 2. From a CentOS command line, enter nmtui to open the interface.
- 3. From the main menu, select **Edit a connection**, and then click **OK**.
- 4. Select the network connection, then click Edit.
- 5. On the **Edit Connection** screen, enter an available static IP address that is not already in use.
- 6. Save the static IP configuration by clicking **OK**, then restart the IBM Spectrum Protect Plus appliance.

#### Related tasks

"Installing IBM Spectrum Protect Plus as a VMware virtual appliance" on page 43
To install IBM Spectrum Protect Plus in a VMware environment, deploy an Open Virtualization Format (OVF) template. Deploying an OVF template creates a virtual appliance containing the application on a VMware host such as an ESXi server.

"Installing IBM Spectrum Protect Plus as a Hyper-V virtual appliance" on page 44
To install IBM Spectrum Protect Plus in a Microsoft Hyper-V environment, import the IBM Spectrum
Protect Plus for Hyper-V template. Importing a template creates a virtual appliance that contains the IBM
Spectrum Protect Plus application on a Hyper-V virtual machine. A local vSnap server that is already
named and registered is also installed on the virtual appliance.

# Uploading the product key

IBM Spectrum Protect Plus runs in an evaluation mode for a limited time period. A valid product key is required to enable IBM Spectrum Protect Plus features indefinitely.

### Before you begin

Save the product key to a computer with internet access and record the location of the key.

### **Procedure**

To upload the product key, complete the following steps:

1. From a supported browser, enter the following URL:

https://HOSTNAME:8090/

Where HOSTNAME is the IP address of the virtual machine where the application is deployed.

2. In the login window, select **Authentication Type** > **System**. Enter the serveradmin password to access the Administration Console. The default password is sppDP758.

You are prompted to enter a new password to access the Administrative Console upon first log in.

- 3. Click Manage your licenses.
- 4. Click **Choose File**, and then browse for the product key on your computer,
- 5. Click Upload new license.
- 6. Click Logout.

### What to do next

After you upload the product key, complete the following action:

Action	How to
Start IBM Spectrum Protect Plus from a supported web browser.	See <u>"Start IBM Spectrum Protect Plus" on page 69</u> .

# **Editing firewall ports**

Use the provided examples as a reference for opening firewall ports on remote VADP proxy servers or application servers. You must restrict port traffic to only the required network or adapters.

### Red Hat Enterprise Linux 7 and later, and CentOS 7 and later

Use the following commands to open ports on remote VADP proxy servers or application servers.

Use the following command to list the open ports:

```
firewall-cmd --list-ports
```

Use the following command to list zones:

```
firewall-cmd --get-zones
```

Use the following command to list the zone that contains the Ethernet port eth0:

```
firewall-cmd --get-zone-of-interface=eth0
```

Use the following command to open port 8098 for TCP traffic. This command is not permanent.

```
firewall-cmd --add-port 8098/tcp
```

Use the following command to open port 8098 for TCP traffic after you restart the firewall rules. Use this command to make the changes persistent:

```
firewall-cmd --permanent --add-port 8098/tcp
```

To undo the change to the port, use this command:

```
firewall-cmd --remove-port 8098/tcp
```

Use the following command to open a range of ports:

```
firewall-cmd --permanent --add-port 60000-61000/tcp
```

Use the following command to reload the firewall rules with the firewall updates:

```
firewall-cmd --reload
```

### **SUSE Linux Enterprise Server 12**

Edit the SUSE Linux Enterprise Server 12 advanced security firewalls options from the **Security and Users** menu. Specify the new port range that you require and apply the changes.

## Firewall configurations that use IP tables

The iptables utility is available on most Linux distributions to enable firewall rules and policy settings. These Linux distributions include Red Hat Enterprise Linux 6.8, Red Hat Enterprise Linux 7 and later, CentOS 7 and later, and SUSE Linux Enterprise Server 12. Before you use these commands, check which firewall zones are enabled by default. Depending upon the zone setup, the INPUT and OUTPUT terms might have to be renamed to match a zone for the required rule.

For Red Hat Enterprise Linux 7 and later, see the following example commands:

Use the following command to list the current firewall policies:

```
sudo iptables -S sudo iptables -L
```

Use the following command to open port 8098 for inbound TCP traffic from an internal subnet <172.31.1.0/24>:

```
sudo iptables -A INPUT -p tcp -s 172.31.1.0/24 --dport 8098 -j ACCEPT
```

Use the following command to open port 8098 for outbound TCP traffic to internal subnet <172.31.1.0/24>:

```
sudo iptables -A OUTPUT -p tcp -d 172.31.1.0/24 --sport 8098 -j ACCEPT
```

Use the following command to open port 8098 for outbound TCP traffic to external subnet <10.11.1.0/24> and only for Ethernet port adapter eth1:

```
sudo iptables -A OUTPUT -o eth1 -p tcp -d 10.11.1.0/24 --sport 8098 -j ACCEPT
```

Use the following command to open port 8098 for inbound TCP traffic to a range of CES IP addresses (10.11.1.5 through 10.11.1.11) and only for Ethernet port adapter eth1:

```
sudo iptables -A INPUT -i eth1 -p tcp -m iprange --dst-range 10.11.1.5-10.11.1.11 --dport 8098 - j ACCEPT
```

Use the following command to allow an internal network, Ethernet port adapter eth1 to communicate with an external network Ethernet port adapter eth0:

```
sudo iptables -A FORWARD -i eth1 -o eth0 -j ACCEPT
```

. This example is for Red Hat Enterprise Linux 7 and later specifically.

Use the following command to open port 8098 for inbound traffic from subnet 10.18.0.0/24 on Ethernet port eth1 within the public zone:

```
iptables -A IN_public_allow -i eth1 -p tcp -s 10.18.0.0/24 --dport 8098 -j ACCEPT
```

Use the following command to save firewall rule changes to persist after a firewall restart process:

```
sudo iptables-save
```

Use the following command to stop and start Uncomplicated Firewall (UFW):

```
service iptables stop service iptables start
```

# **Installing iSCSI initiator utilities**

You must install Internet Small Computer System Interface (iSCSI) utilities if iSCSI mounted storage devices are directly connected to the IBM Spectrum Protect Plus appliance or to a vSnap server. After the iSCSI initiator utilities are installed, iSCSI mounted storage devices can be connected to the appliance or server on which the package is installed.

### **About this task**

iSCSI initiator utilities can be installed on the IBM Spectrum Protect Plus appliance or a vSnap server. The iSCSI initiator utilities are delivered along with IBM Spectrum Protect Plus, but are not installed automatically. To install the utilities, follow the procedure.

### **Procedure**

- 1. Log on to the appliance or server that is to be directly connected to the iSCSI mounted storage.
  - For the IBM Spectrum Protect Plus appliance, use the Secure Shell (SSH) protocol and authenticate with the appropriate administrative credentials.
  - For a vSnap server, use SSH or access the server directly and authenticate with the appropriate administrative credentials.
- 2. Install the iSCSI initiator utilities by running the following command:

```
sudo /usr/bin/yum --disablerepo=* --enablerepo=base,updates install iscsi-initiator-utils
```

# Chapter 3. Installing and configuring vSnap servers

Every installation of IBM Spectrum Protect Plus requires at least one vSnap server, which is the primary backup destination.

In both VMware and Hyper-V environments, one vSnap server with the name localhost is automatically installed when the IBM Spectrum Protect Plus appliance is initially deployed. An onboard vSnap server resides on a partition of the IBM Spectrum Protect Plus appliance and is registered and initialized in IBM Spectrum Protect Plus. In smaller backup environments, the onboard vSnap server might be sufficient.

In larger enterprise environments, additional vSnap servers might be required. For guidance about sizing, building, and placing vSnap servers and other components in your IBM Spectrum Protect Plus environment, see the IBM Spectrum Protect Plus Blueprints.

Additional vSnap servers can be installed on either virtual or physical appliances any time after the IBM Spectrum Protect Plus appliance is installed and deployed. After installation, some registration and configuration steps are required for these stand-alone vSnap servers.

The process for setting up a stand-alone vSnap server is as follows:

- 1. Install the vSnap server.
- 2. Add the vSnap server as Disk Storage in IBM Spectrum Protect Plus.
- 3. Initialize the system and create a storage pool.

# **Installing vSnap servers**

When you deploy an IBM Spectrum Protect Plus appliance, a vSnap server is automatically installed. This server is the primary backup destination. In larger enterprise environments, additional vSnap servers might be required.

### Before you begin

Complete the following steps:

- 1. Review the vSnap system requirements in "Component requirements" on page 11.
- 2. Download the installation package. Different installation files are provided for installation on physical or virtual machines. Ensure that you download the correct files for your environment. For more information about downloading files, see technote 879861.

**Note:** The IBM Spectrum Protect Plus and vSnap appliance is a closed system and anti-virus (AV) installation is not supported on virtual or physical deployments.

**Important:** IBM Spectrum Protect Plus components, including vSnap, should not be installed on the same machine, physical or virtual, as IBM Spectrum Protect Server.

## Installing a physical vSnap server

A Linux operating system that supports physical vSnap installations is required to install a vSnap server on a physical machine.

### **Procedure**

- 1. Install a Linux operating system that supports physical vSnap installations. See <u>"vSnap server physical</u> installation requirements" on page 15 for supported operating systems.
  - The minimum installation configuration is sufficient, but you can also install additional packages including a graphical user interface (GUI). The root partition must have at least 8 GB of free space after installation.
- 2. Edit the /etc/selinux/config file to change the SELinux mode to Permissive.

- 3. Run setenforce 0 to apply the setting immediately without requiring a restart.
- 4. Download the vSnap installation file CC1QGML.run from Passport Advantage Online. For information about downloading files, see technote 879861.
- 5. Make the file executable through the command chmod +x file\_name.run, and then run the executable. The vSnap packages are installed, plus all of required components.

#### What to do next

After you install the vSnap server, complete the following action:

Action	How to
Add the vSnap server to IBM Spectrum Protect Plus and configure the vSnap environment.	See "Managing vSnap servers" on page 54.

# Installing a virtual vSnap server and a VADP proxy in a VMware environment

To install a virtual vSnap server and a vStorage API for Data Protection (VADP) proxy in a VMware environment, deploy an Open Virtualization Format (OVF) template. This creates a machine that contains the vSnap server and the VADP proxy.

### Before you begin

For easier network administration, use a static IP address for the virtual machine. Assign the address by using the NetworkManager Text User Interface (nmtui) tool. For instructions, see <u>"Assigning a static IP</u> address" on page 46, Work with your network administrator when configuring network properties.

### **Procedure**

- 1. Download the server and proxy template installation file CC1QEML. ova from Passport Advantage Online. For information about downloading files, see technote 879861.
- 2. To deploy the vSnap server, take one of the following actions:
  - If you are using the vSphere Client to deploy the vSnap server, from the **File** menu, click **Deploy OVF Template**.
  - If you are using the vSphere Web Client, click **Create/Register VM**, then click **Deploy a virtual** machine from an OVF or OVA file. Click **Next**.
- 3. Specify the location of the CC10EML. ova file and select it. Click **Next**.
- 4. Review the template details and accept the End User License Agreement. Click Next.
- 5. Provide a meaningful name for the template, which becomes the name of your virtual machine. Identify an appropriate location to deploy the virtual machine. Click **Next**.
- 6. Identify the datacenter, server, and resource pool for deployment. When prompted to select storage, select from the datastores that are already configured on the destination host. The virtual machine configuration file and virtual disk files are stored on the datastore. Select a datastore that is large enough to accommodate the virtual machine and all of its virtual disk files. Click **Next**.
- 7. Select a disk format to store the virtual disks. To optimize performance, you can select thick provisioning, which is preselected. Thin provisioning requires less disk space, but might impact performance. Click **Next**.
- 8. Select networks for the deployed template to use. Several available networks on the ESX server may be available by clicking Destination Networks. Select a destination network that allows you to define the appropriate IP address allocation for the virtual machine deployment. Click **Next**.
- 9. Enter network properties for the virtual machine default gateway, DNS, search domain, IP address, network prefix, and machine host name. If you are using a Dynamic Host Configuration Protocol (DHCP) configuration, leave all fields blank.

**Restriction:** A default gateway must be properly configured before deployment of the OVF template. Multiple DNS strings are supported, and must be separated by commas without the use of spaces.

The network prefix should be specified by a network administrator. The network prefix must be entered using CIDR notation; valid values are 1 - 24.

10. Provide details of the VADP configuration, including the IP address of the IBM Spectrum Protect Plus appliance.

For ESXi server 5.5, this prompt is shown when the OVF deployment template reaches the **Properties** step.

For the ESXi server 6.0 and later, this prompt is shown when the OVF deployment template reaches the **Customize Template** step.

- 11. Click Next.
- 12. Review your template selections. Click **Finish** to exit the wizard and to start deployment of the OVF template. Deployment might take significant time.
- 13. After the OVF template is deployed, power on your newly created virtual machine. You can power on the VM from the vSphere Client.

**Important:** The VM must remain powered on for the IBM Spectrum Protect Plus application to be accessible.

14. Record the IP address of the newly created VM.

The IP address is required to access and register the vSnap server. Find the IP address in vSphere Client by clicking the VM and reviewing the **Summary** tab.

### What to do next

After you install the vSnap server, complete the following action:

Action	How to
Add the vSnap server to IBM Spectrum Protect Plus and configure the vSnap environment.	See "Managing vSnap servers" on page 54.
Configure the VADP environment.	See "Setting options for VADP proxies" on page 105.

# Installing a virtual vSnap server in a Hyper-V environment

To install a vSnap server in a Hyper-V environment, import a Hyper-V template. This creates a virtual appliance containing the vSnap server on a Hyper-V virtual machine.

### Before you begin

All Hyper-V servers, including cluster nodes, must have the Microsoft iSCSI initiator service running in their Services list. Set the service to Automatic so that it is available when the machine is restarted.

### **Procedure**

- 1. Download the vSnap installation file CC1QFML.exe from Passport Advantage Online. For information about downloading files, see technote 879861.
- 2. Copy the installation file to your Hyper-V server.
- 3. Start the installer and complete the installation steps.
- 4. Open Hyper-V Manager and select the required server. For Hyper-V system requirements, see System requirements for Hyper-V on Windows Server.
- 5. From the **Actions** menu in Hyper-V Manager, click **Import Virtual Machine**, and then click **Next**. The **Locate Folder** dialog opens.
- 6. Browse to the location of the Virtual Machines folder within the unzipped vSnap folder. Click **Next**. The **Select Virtual Machine** dialog opens.
- 7. Select vSnap, and then click **Next**. The **Choose Import Type** dialog opens.
- 8. Choose the following import type: Register the virtual machine in place. Click Next.
- 9. If the Connect Network dialog opens, specify the virtual switch to use, and then click **Next**. The Completing Import dialog opens.

- 10. Review the description, and then click **Finish** to complete the import process and close the **Import Virtual Machine** wizard. The virtual machine is imported.
- 11. Right-click the newly deployed VM, and then click **Settings**.
- 12. Under the section named IDE Controller 0, select Hard Drive.
- 13. Click Edit, and then click Next.
- 14. In the Choose Action screen, choose Convert then click Next.
- 15. For the Disk Format, select VHDX.
- 16. For the Disk Type, select Fixed Size.
- 17. For the Configure Disk option, give the disk a new name and optionally, a new location.
- 18. Review the description, and then click **Finish** to complete the conversion.
- 19. Click **Browse**, and then locate and select the newly created VHDX.
- 20. Repeat steps 12 through 18 for each disk under the SCSI Controller section.
- 21. Power on the VM from **Hyper-V Manager**. If prompted, select the option where the kernel starts in rescue mode.
- 22. Use Hyper-V Manager to identify the IP address of the new virtual machine if automatically assigned. To assign a static IP to the virtual machine using NetworkManager Text User Interface, see the following section.
- 23. If the address of the new VM is automatically assigned, use Hyper-V Manager to identify the IP address. To assign a static IP to a VM, use the NetworkManager Text User Interface (nmtui) tool. For instructions, see "Assigning a static IP address" on page 46.

### What to do next

After you install the vSnap server, complete the following action:

Action	How to
Add the vSnap server to IBM Spectrum Protect Plus and configure the vSnap environment.	See "Managing vSnap servers" on page 54.

# **Managing vSnap servers**

To enable backup and restore jobs, at least one IBM Spectrum Protect Plus virtual appliance and at least one vSnap server is required. The vSnap server can be located on the IBM Spectrum Protect Plus appliance or on its own appliance, or it can be a physical vSnap installation. Each vSnap server location must be added so that IBM Spectrum Protect Plus recognizes it.

# Adding a vSnap server as a backup storage provider

The onboard vSnap server is registered in IBM Spectrum Protect Plus when the appliance is deployed. You must add any additional servers that are installed on either virtual or physical appliances so that they are recognized by IBM Spectrum Protect Plus.

### Before you begin

After you add a vSnap server as a backup storage provider, you might have to configure and administer certain aspects of vSnap, such as network configuration or storage pool management. For more information, see "vSnap server administration reference" on page 60.

### **Procedure**

To add a vSnap server as a backup storage device, complete the following steps:

- 1. Log on to the vSnap server console with the user ID serveradmin. The initial password is sppDP758. You are prompted to change this password during the first logon.
- 2. Run the **vsnap user create** command to create a user name and password for the vSnap server.

- 3. Start the IBM Spectrum Protect Plus user interface by entering the host name or IP address of the virtual machine where IBM Spectrum Protect Plus is deployed in a supported browser.
- 4. In the navigation pane, click System Configuration > Backup Storage > Disk.
- 5. Click Add Disk Storage.
- 6. Complete the fields in the **Storage Properties** pane:

### Hostname/IP

Enter the resolvable IP address or hostname of the backup storage.

#### Site

Select a site for the backup storage. Available options are **Primary**, **Secondary**, or **Add a new site**. If more than one primary, secondary, or user-defined site is available to IBM Spectrum Protect Plus, the site with the largest amount of available storage is used first.

#### Username

Enter the user name for the vSnap server that you created in step "2" on page 54.

### **Password**

Enter the password for the user.

### 7. Click Save.

IBM Spectrum Protect Plus confirms a network connection and adds the backup storage device to the database.

### What to do next

After you add a backup storage provider, take the following actions:

Action	How to
Initialize the vSnap server.	See "Initializing the vSnap server" on page 56.
Expand the vSnap storage pool.	See "Expanding a vSnap storage pool" on page 58.
If necessary, configure and administer certain aspects of vSnap, such as network configuration or storage pool management.	"vSnap server administration reference" on page 60

### **Related tasks**

"Start IBM Spectrum Protect Plus" on page 69

Start IBM Spectrum Protect Plus to begin using the application and its features.

## Editing settings for a vSnap server

You can edit the configuration settings for a vSnap server to reflect changes in your IBM Spectrum Protect Plus environment.

### **Procedure**

To edit the settings for a vSnap server, complete the following steps:

- 1. In the navigation pane, click System Configuration > Backup Storage > Disk.
- 2. Click the edit icon / that is associated with a vSnap server.

The **Edit Storage** pane is displayed.

3. Revise the vSnap server settings, and then click **Save**.

### Deleting a vSnap server

You can delete a vSnap server that is no longer used in your IBM Spectrum Protect Plus environment.

### Before you begin

When a vSnap server is deleted, all recovery points that are associated with the vSnap server are purged from IBM Spectrum Protect Plus during the next maintenance job.



**Attention:** Deletion of a vSnap server can result in loss of data.

Before you delete a vSnap server, review the scenarios to determine whether deletion is appropriate or whether other action must be taken.

**Scenario 1**: The vSnap server is temporarily down due to storage or network issues.

- Do not delete the vSnap server. If you delete the vSnap server, recovery points that are associated with the server will be purged and backups will be rebased.
- Complete the necessary storage or network maintenance to bring the vSnap server back online.

**Scenario 2**: The vSnap server is assigned a new host name or IP address.

- Do not delete the vSnap server. If you delete the vSnap server, recovery points that are associated with the server will be purged and backups will be rebased.
- Edit the settings for the vSnap server to specify the new host name or IP address. To edit the settings for a vSnap server, follow the instructions "Editing settings for a vSnap server" on page 55.

Scenario 3: The vSnap server is not in use, and there are no plans to reuse it.

- Delete the vSnap server and run a maintenance job to ensure that recovery points that are associated with the vSnap server are purged from IBM Spectrum Protect Plus.
  - Incremental backups of the data that was present on the vSnap server will no longer be possible.
  - Recovering data that was present on the vSnap server will no longer be possible.
- Subsequent runs of backup jobs will automatically create new volumes on another vSnap server in the same site and will perform new base backups.

**Scenario 4**: The vSnap pool is lost and you want to build a new pool on the same vSnap server.

- 1. Delete the vSnap server and run a maintenance job to ensure that recovery points that are associated with the old vSnap pool are purged from IBM Spectrum Protect Plus.
  - Incremental backups of the data that was present in the old pool will no longer be possible.
  - Recovering data that was present in the old pool will no longer be possible.
- 2. On the vSnap server, create a pool.
- 3. Add the vSnap server back into IBM Spectrum Protect Plus. To add a vSnap server to IBM Spectrum Protect Plus, see "Adding a vSnap server as a backup storage provider" on page 54.
  - Subsequent runs of backup jobs will automatically create volumes on this or another vSnap server in the same site and will perform new base backups.

### **Procedure**

To delete a vSnap server, complete the following steps:

- 1. In the navigation pane, click System Configuration > Backup Storage > Disk.
- 2. Click the delete icon X that is associated with a vSnap server.
- 3. Click **Yes** to delete the server from IBM Spectrum Protect Plus.

## Initializing the vSnap server

The initialization process prepares a new vSnap server for use by loading and configuring software components and initializing the internal configuration. This is a one-time process that you must run only for new installations.

#### **About this task**

As part of the initialization process, vSnap creates a storage pool using any available unused disks on the system. The OVA-based deployments of vSnap each contain a default 100 GB unused virtual disk which is used to create the pool.

If no unused disks are found, the initialization process completes without creating a pool.

For information about how to expand, create, and administer storage pools, see <u>"Storage management"</u> on page 61.

You can use the IBM Spectrum Protect Plus user interface or the vSnap server console to initialize vSnap servers.

For servers that are deployed in a virtual environment, the user interface provides a simple method to run the initialization operation.

For servers that are deployed in a physical environment, the vSnap server console offers more options for initializing the server, including the ability to create a storage pool by using advanced redundancy options and a specific list of disks.

# Completing a simple initialization

To prepare a vSnap server for use, you must initialize the vSnap server. Use the IBM Spectrum Protect Plus to initialize a vSnap server that is deployed in a virtual environment.

### **About this task**

For the onboard vSnap installation that is registered as part of an IBM Spectrum Protect Plus installation, you are prompted to start the initialization process the first time you log in to the user interface. No further steps are required.

#### **Procedure**

To initialize a vSnap server by using the IBM Spectrum Protect Plus user interface, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Backup Storage** > **Disk**.
- 2. From the **Actions** menu that is associated with the server, select the initialization method:

## **Initialize with Encryption**

Enable encryption of backup data on the vSnap server.

### **Initialize**

Initialize the vSnap server without encryption enabled.

The initialization process runs in the background and requires no further user interaction. The process might take 5 - 10 minutes to complete.

# Completing an advanced initialization

Use the vSnap server console to initialize a vSnap server that is deployed in a physical environment. Initializing by using the vSnap server console offers more options for initializing the server, including the ability to create a storage pool by using advanced redundancy options and a specific list of disks.

### **Procedure**

To initialize a vSnap server by using the vSnap server console, complete the following steps:

- 1. Log in to the vSnap server console with the user ID serveradmin. The initial password is sppDP758. You can also use a user ID that has vSnap admin privileges that you create by using the vsnap user create command. For more information about using console commands, see "vSnap server administration reference" on page 60.
- 2. Run the **vsnap system init --skip\_pool** command. The command requires no further interaction and completes all initialization tasks except for the creation of a storage pool. The process might take 5 10 minutes to complete.

### What to do next

After you complete the initialization, complete the following action:

Action	How to
Create a storage pool	See <u>"Storage management"</u> on page 61.

# Setting vSnap storage options

You can set additional storage-related options for a vSnap server.

#### **Procedure**

To set the options for a vSnap server, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Backup Storage** > **Disk**.
- 2. Click the manage icon that is associated with the vSnap server, and then expand the **Storage**Options section. Set the storage options.

### **Enable Compression**

If enabled, each incoming block of data is compressed using a compression algorithm before it is written to the storage pool. Compression consumes a moderate amount of additional CPU resources.

### **Enable Deduplication**

If enabled, each incoming block of data is hashed and compared against existing blocks in the storage pool. If compression is enabled, the data is compared after it is compressed. Duplicate blocks are skipped instead of being written to the pool. Deduplication is disabled by default because it consumes a large amount of memory resources (proportional to the amount of data in the pool) to maintain the deduplication table of block hashes.

### **Encryption Enabled**

This option displays the encryption status of the vSnap server. Encryption can be enabled only during vSnap initialization. This option is for informational purposes only.

#### **Concurrent Backup**

This option controls how many parallel backup streams are sent to the vSnap server across multiple jobs running concurrently. For application backups, each database is treated as a single stream. For hypervisor backups, each virtual disk is treated a single stream. The available concurrent backups options can be used to prevent multiple or large SLA policies from sending too many data streams to a small vSnap server that may not be able to accommodate the load.

Set this option to Unlimited, Pause, or Limit for concurrent backups to save time. If the Limit option is selected, enter an integer for the number of concurrent backups. The default setting is 1000.

3. Click Save.

# Expanding a vSnap storage pool

If IBM Spectrum Protect Plus reports that a vSnap server is reaching its storage capacity, the vSnap storage pool must be expanded. To expand a vSnap storage pool, you must first add virtual or physical disks on the vSnap server, either by adding virtual disks to the vSnap virtual machine or adding physical disks to the vSnap physical server. See the vSphere documentation for information about creating additional virtual disks.

# Before you begin

Virtual or physical disks must be added to the vSnap server prior to this procedure. Expanding existing volumes is not supported.

### **Procedure**

To expand a vSnap storage pool, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Backup Storage** > **Disk**.
- 2. Select **Actions** > **Rescan** for the vSnap server that you want to rescan.

- 3. Click the manage icon \* that is associated with the vSnap server, and then expand the **Add New Disks to Backup Storage** section.
- 4. Add and save the selected disks. The vSnap pool expands by the size of the disks that are added.

# Establishing a replication partnership for a vSnap server

By using backup storage replication, you can asynchronously backup data from one vSnap server to another.

### Before you begin

All vSnap servers must be at the same version level for replication to function. Replication between different versions is not supported.

### **Procedure**

To establish a replication partnership, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Backup Storage** > **Disk**.
- 2. Click the manage icon \*\* that is associated with the vSnap server that you want to add a replication partnership to, and then expand the **Configure Storage Partners** section.
- 3. Click the add icon 🛂.
- 4. From the **Select Partner** list, select a vSnap server with which to establish a replication partnership.
- 5. Click Add Partner.

### What to do next

After you create a replication partnership, complete the following action to enable replication:

Action	How to
Select the <b>Backup Storage Replication</b> option in the SLA policy that is associated with the backup job.	See "Creating an SLA policy" on page 87

# Changing offload throughput rate

Change the throughput for site replication and offload operations so that you can manage your network activity on a defined schedule.

### **Procedure**

- 1. In the navigation pane, click **System Configuration** > **Site** to open the **Site Properties** pane.
- 2. Click the edit icon that is associated with the site for which you want to change the throughput.
- 3. Click Enable Throttle.

The rate of the throughput is displayed in MB/s.

- 4. Adjust the throughput:
  - Change the rate of throughput with the up and down arrows.
  - Change the data value. The choices include Bytes/s, KB/s, MB/s, or GB/s.




Figure 4. Enabling different throttles for different times to improve throughput

5. Select times for the changed throughput in the weekly schedule table, or specify a day and time for the changed rate.

**Note:** To clear a timeslot, click the timeslot. The scheduled selections are listed underneath the schedule table.

6. Click **Save** to commit the changes and close the panel.

# vSnap server administration reference

After the vSnap server is installed, registered, and initialized, IBM Spectrum Protect Plus automatically manages its use as a backup target. Volumes and snapshots are created and managed automatically based on the SLA policies that are defined in IBM Spectrum Protect Plus.

You might need to configure and administer certain aspects of vSnap, such as network configuration or storage pool management.

### Managing vSnap by using the command line interface

The vSnap command-line interface is the primary means of administering vSnap. Run the **vsnap** command to access the command line interface. The command can be run by the user ID serveradmin or any other operating system user who has vSnap admin privileges. Use the **vsnap user create** command to create more operating system users that have these privileges. The initial serveradmin password is sppDP758.

The command line interface consists of several commands and sub-commands that manage various aspects of the system. See "Storage management" on page 61 and "Network management" on page 63 for details on using these commands. You can also pass the --help flag to any command or subcommand to view usage help, for example, vsnap --help or vsnap pool create --help.

# Managing vSnap by using the IBM Spectrum Protect Plus user interface

Some of the most common operations can also be completed from the IBM Spectrum Protect Plus user interface. Log in to the user interface and click **System Configuration** > **Backup Storage** > **Disk** in the navigation pane. Click the manage icon for a vSnap server to manage it.

## **Related tasks**

# "Installing vSnap servers" on page 51

When you deploy an IBM Spectrum Protect Plus appliance, a vSnap server is automatically installed. This server is the primary backup destination. In larger enterprise environments, additional vSnap servers might be required.

# "Managing vSnap servers" on page 54

To enable backup and restore jobs, at least one IBM Spectrum Protect Plus virtual appliance and at least one vSnap server is required. The vSnap server can be located on the IBM Spectrum Protect Plus appliance or on its own appliance, or it can be a physical vSnap installation. Each vSnap server location must be added so that IBM Spectrum Protect Plus recognizes it.

# Storage management

You can configure and administer storage pools for a vSnap server.

# **Managing disks**

vSnap creates a storage pool using disks provisioned to the vSnap server. In the case of virtual deployments, the disks can be RDM or virtual disks provisioned from datastores on any backing storage. In the case of physical deployments, the disks can be local or SAN storage attached to the physical server. The local disks may already have external redundancy enabled via a hardware RAID controller, but if not, vSnap can also create RAID-based storage pools for internal redundancy.

Disks that are attached to vSnap servers must be thick provisioned. If disks are thin provisioned, the vSnap server will not have an accurate view of free space in the storage pool, which might lead to data corruption if the underlying datastore runs out of space.



**Attention:** Once a disk has been added to a storage pool, it should not be removed. Removing a disk will corrupt the storage pool.

If vSnap was deployed as part of a virtual appliance, it already contains a 100 GB starter virtual disk that can be used to create a pool. You can add more disks before or after creating a pool and accordingly use them to create a larger pool or expand an existing pool. If job logs report that a vSnap server is reaching its storage capacity, additional disks can be added to the vSnap pool. Alternatively, creating new SLA policies will force backups to use an alternate vSnap.

It is essential to protect against corruption caused by a VMware datastore on a vSnap server reaching its capacity. Create a stable environment for virtual vSnap servers that do not use RAID configurations by utilizing thick provisioned VMDKs. Replicating to external vSnap servers provides further protection.

A vSnap server will become invalidated if the vSnap pool is deleted or if a vSnap disk is deleted in a non-redundant RAID configuration. All data on the vSnap server will be lost. If your vSnap server becomes invalidated you must unregister the vSnap server using the IBM Spectrum Protect Plus interface, then run the maintenance job. Once complete, the vSnap server can be re-registered.

# **Managing encryption**

To enable encryption of backup data on a vSnap server, select **Initialize with encryption enabled** when you initialize the server. Encryption settings cannot be changed after the server is initialized and a pool is created. All disks of a vSnap pool use the same encryption key file, which is generated upon pool creation. Data is encrypted when at rest on the vSnap server.

vSnap encryption utilizes the following algorithm:

#### Cipher name

Advanced Encryption Standard (AES)

# Cipher mode

xts-plain64

Key

256 bits

# Linux Unified Key Setup (LUKS) header hashing

sha256

# **Managing encryption keys**

The disk encryption key files generated upon pool creation are stored under the directory /etc/vsnap/ keys/ on each vSnap server. For disaster recovery purposes, back up the key files manually outside the vSnap server. After a pool is created, use the following commands as the serveradmin user to copy them to a temporary location and then copy them to a desired, secure backup location outside the vSnap host.

mkdir /tmp/keybackup-\$(hostname)

sudo cp -r /etc/vsnap/keys /tmp/keybackup-\$(hostname)

# **Detecting disks**

If you add disks to a vSnap server, use the command line or the IBM Spectrum Protect Plus user interface to detect the newly attached disks.

**Command line:** Run the **vsnap disk rescan** command.

**User interface:** Click **System Configuration** > **Backup Storage** > **Disk** in the navigation pane, and then click the **Actions** menu next to the relevant vSnap server and select **Rescan**.

# **Showing disks**

Run the vsnap disk show command to list all disks that are on the vSnap system,

The USED AS column in the output shows whether each disk is in use. Any disk that is unformatted and unpartitioned is marked as unused, otherwise they are marked as used by the partition table or file system that is discovered on them.

Only disks that are marked as unused are eligible for creating or adding to a storage pool. If a disk that you plan to add to a storage pool is not seen as unused by vSnap, it might be because it was previously in use and thus contains remnants of an older partition table or file system. You can correct this by using system commands like **parted** or **dd** to wipe the disk partition table.

# **Showing storage pool information**

Run the **vsnap pool show** command to view information about each storage pool.

# Creating a storage pool

If you completed the simple initialization procedure described in <u>"Completing a simple initialization" on</u> page 57, a storage pool was created automatically and the information in this section is not applicable.

To complete an advanced initialization, use the **vsnap pool create** command to create a storage pool manually. Before you run the command, ensure that one or more unused disks are available as described in <u>"Showing disks" on page 62</u>. For information about available options, pass the **--help** flag for any command or subcommand.

Specify a user-friendly display name for the pool and a list of one or more disks. If no disks are specified, all available unused disks are used. You can choose to enable compression and deduplication for the pool during creation. You can also update the compression/deduplication settings at a later time by using the **vsnap pool update** command.

The pool type that you specify during the creation of the storage pool dictates the redundancy of the pool:

#### raid0

This is the default option when no pool type is specified. In this case vSnap assumes your disks have external redundancy, for example, if you use virtual disks on a datastore backed by redundant storage. In this case, the storage pool will have no internal redundancy.

Once a disk has been added to a raid0 pool it cannot be removed. Disconnecting the disk will result in the pool becoming unavailable, which can be resolved only by destroying and recreating the pool.

## raid5

When you select this option, the pool is comprised of one or more RAID5 groups each consisting of three or more disks. The number of RAID5 groups and the number of disks in each group depends on the total number of disks you specify during pool creation. Based on the number of available disks, vSnap chooses values that maximize total capacity while also ensuring optimal redundancy of vital metadata.

#### raid6

When you select this option, the pool is comprised of one or more RAID6 groups each consisting of four or more disks. The number of RAID6 groups and the number of disks in each group depends on the total number of disks that you specify during pool creation. Based on the number of available disks, vSnap chooses values that maximize total capacity while also ensuring optimal redundancy of vital metadata.

# Expanding a storage pool

Before expanding a pool, ensure that one or more unused disks are available as described in <u>"Showing</u> disks" on page 62.

Use the command line or the IBM Spectrum Protect Plus user interface to expand a storage pool.

**Command line:** Run the **vsnap pool expand** command. For information about available options, pass the **--help** flag for any command or subcommand.

User interface: Click System Configuration > Backup Storage > Disk in the navigation pane. Click the manage icon for a vSnap server to manage it, and then expand the Add New Disks tab. The tab displays all unused disks discovered on the system. Select one or more disks and click Save to add them to the storage pool.

# **Network management**

Configure and administer network services for a vSnap server.

# **Showing network interface information**

Run the **vsnap network show** command to list network interfaces and the services that are associated with each interface.

By default, the following vSnap services are available of all network interfaces:

#### mgmt

This service is used for management traffic between IBM Spectrum Protect Plus and vSnap.

#### nfs

This service is used for data traffic when backing up data using NFS.

# iscsi

This service is used for data traffic when backing up data using iSCSI.

#### smb

This service is used for data traffic when backing up data using SMB/CIFS.

## repl

This service is used for data traffic between vSnap servers during replication.

# Modifying services associated with network interfaces

Run the **vsnap network update** command to modify services that are associated with an interface. For example, if you are using a dedicated interface for data traffic to improve performance.

The following options are required:

#### --id <id>

Enter the ID of the interface to update.

#### --services <services>

Specify all or a comma-separated list of services to enable on the interface. The following are valid values: mgmt, nfs, smb, and iscsi.

If a service is available on more than one interface, IBM Spectrum Protect Plus can use any one of the interfaces.

Ensure that the mgmt service remains enabled on the interface that was used to register the vSnap server in IBM Spectrum Protect Plus.

# Preventing job failures by synchronizing vSnap and CIFS passwords

Communications between a vSnap server and a Common Internet File System (CIFS) share can be disrupted if credentials are shared, but passwords are out of sync. To prevent jobs from failing, you must synchronize the vSnap and CIFS passwords.

#### **About this task**

When you synchronize credentials, the vSnap password is changed to the CIFS share password. In the procedure, the user name *vsnapuser* is used as an example.

#### **Procedure**

- 1. Log on to the vSnap server console with the user ID serveradmin. The initial password is sppDP758.
- 2. Update the operating system credentials that are used for communication management with the vSnap API by opening a command prompt and issuing the following command.

sudo passwd vsnapuser

3. Using the same password from Step 2, update the CIFS credentials that are used for communication on the vSnap server by issuing the following command:

sudo smbpasswd vsnapuser

4. Update the vSnap server registration in the IBM Spectrum Protect Plus appliance. Set the **Password** parameter to match the new password. For more information on editing vSnap settings, see <u>"Editing</u> settings for a vSnap server" on page 55.

#### **Results**

Communication between the vSnap server and CIFS shares is established after password resynchronization. Rerun any jobs that failed because the passwords were not synchronized.

# Uninstalling a vSnap server

You can remove a vSnap server from your IBM Spectrum Protect Plus environment.

#### Before you begin

Ensure that no jobs use SLA policies that define the vSnap server as a backup location. To view the SLA policies that are associated with jobs, see the **Backup** page for the hypervisor or application that is

scheduled for backup. For example, for VMware backup jobs, click **Manage Protection > Hypervisors > VMware**.

#### **Procedure**

1. Log on to the vSnap server console with the user ID serveradmin. The initial password is sppDP758.

You can also use a user ID that has vSnap administrator privileges that you create by using the **vsnap user create** command. For more information about using console commands, see <u>"vSnap server</u> administration reference" on page 60.

2. Run the following commands:

```
systemctl stop vsnap
yum remove vsnap
```

3. Optional: If you do not plan to reinstall the vSnap server after it is uninstalled, remove the data and configuration by running the following commands:

```
rm -rf /etc/vsnap
rm -rf /etc/nginx
rm -rf /etc/uwsgi.d
rm -f /etc/uwsgi.ini
```

4. Reboot the system to ensure kernel modules are unloaded and detach the data disks containing vSnap pool data.

**Note:** To uninstall IBM Spectrum Protect Plus in a Hyper-V environment, delete the IBM Spectrum Protect Plus appliance from Hyper-V and then delete the installation directory.

# **Results**

After a vSnap server is uninstalled, the configuration is retained in the /etc/vsnap directory. The configuration is reused if the vSnap server is reinstalled. The configuration is removed if you ran the optional commands to remove the configuration data.

# Chapter 4. Getting off to a quick start

To start using IBM Spectrum Protect Plus, you must complete steps that include defining resources that you want to protect and creating service level agreement (SLA) policies, also known as backup policies, for those resources. This getting started section provides the basic steps to set up and start using IBM Spectrum Protect Plus to back up data. Other tasks such as offloading and restoring data are discussed in detail in other areas of the documentation.

Before you start, ensure that you followed the instructions in the <u>IBM Spectrum Protect Plus Blueprints</u> to determine how to size, build, and place the components in your IBM Spectrum Protect Plus environment and that the tasks listed in the "Product deployment roadmap" on page 11 are complete.

As shown in the following table, the initial installation and configuration tasks are completed by the IBM Spectrum Protect Plus *infrastructure administrator*. By default, the admin user account is created for use by the infrastructure administrator to start the application for the first time.

Then, hypervisor and database application backup and restore tasks are completed by the *application administrator*. However, a single administrator might be responsible for all tasks in your environment.

Action	Owner	
Start IBM Spectrum Protect Plus	Infrastructure administrator and application administrator	The infrastructure administrator starts the application for the first time by using the default admin user account with the password password. The administrator is prompted to reset the user name for this account after logging in. The administrator cannot reset the user name to admin, root, or test.
		After the initial startup, the application administrator can start the application by using this user account or another account that the infrastructure administrator creates.

Action	Owner	
"Manage sites" on page 69	Infrastructure administrator	A site is used to group vSnap servers based on a physical or logical location to help quickly identify and interact with backup data. A site is assigned to a vSnap server when the server is added to IBM Spectrum Protect Plus.
		The default sites are named Primary and Secondary, but a custom site can also be created and assigned when the vSnap server is added.
		Before continuing to the following actions, review the available sites and determine whether you want to add new sites or modify the existing ones.
Create backup policies	Infrastructure administrator	Backup policies define the parameters that are applied to backup jobs. These parameters include the frequency and retention of backups and the options to replicate data from one vSnap server to another and to offload backup data to secondary backup storage for longer-term protection.
		Backup policies also define the target site to for backing up data. A site can contain one or more vSnap servers.
		Backup policies are called SLA policies in IBM Spectrum Protect Plus.
Create a user account for the application administrator	Infrastructure administrator	User accounts determine the resources and functions that are available to the user.
Add resources to protect	Application administrator	Resources are servers for hypervisors or database applications that host data that you want to protect.
Add resources to a job definition	Application administrator	Job definitions associate the resources that you want to protect with one or more SLA policies. The options and schedules that are defined in the SLA policies are used for backup jobs for the resources.

Action	Owner	
Start a backup job	Application administrator	Backup jobs are started as defined in the SLA policy that is associated with the job definition. You can also manually start a job.
Run a report	Application administrator	IBM Spectrum Protect Plus provides a number of predefined reports that you can run with default parameters or modify to create custom reports.

# **Start IBM Spectrum Protect Plus**

Start IBM Spectrum Protect Plus to begin using the application and its features.

#### **Procedure**

To start IBM Spectrum Protect Plus, complete the following steps:

1. In a supported web browser, enter the following URL:

https://host\_name

Where *host\_name* is the IP address of the virtual machine where the application is deployed. This connects you to IBM Spectrum Protect Plus.

2. Enter your user name and password to log on.

If this is your first time logging on, the default user name is admin and the password is password. You are prompted to reset the default user name and password. You cannot reset the user name to admin, root, or test.

- 3. Click Sign In.
- 4. If you are logging on to IBM Spectrum Protect Plus for the first time, you are prompted to complete the following actions:
  - Change the serveradmin password. The initial password is sppDP758. The serveradmin user is used to access the administrative console and the IBM Spectrum Protect Plus virtual appliance. The the password for serveradmin must be changed before accessing the administrative console and IBM Spectrum Protect Plus virtual appliance.
  - Start the initialization process for the onboard vSnap server. Select **Initialize** or **Inititalize with encryption enabled** to encrypt data on the server.

# **Manage sites**

A site is used to group vSnap servers based on a physical or logical location to help quickly identify and interact with backup data. A site is assigned to a vSnap server when the server is added to IBM Spectrum Protect Plus.

# About this task

A site is assigned to a vSnap server when the server is added to IBM Spectrum Protect Plus. Review the available sites by clicking **System Configuration** > **Site** in the navigation pane and decide whether you want to add new sites or edit the existing ones for your vSnap servers.

Note: You can change the site name and other options for the default Primary and Secondary sites.

The Demo site is available only for the onboard vSnap server. You cannot use this site with any other vSnap server.

#### **Procedure**

To add or edit a site, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Site**.
- 2. To add new sites or edit existing sites, take the appropriate action:

Action	How to
Add a new site.	a. Click <b>Add Site</b> . b. Enter a site name.
	<ul> <li>c. Optional: Select <b>Enable Throttle</b> to manage the throughput for site replication and offload operations as described in "Adding a site" on page 249.</li> <li>d. Click <b>Save</b>.</li> </ul>
Edit a site.	a. Click <b>Edit Site</b> .
	b. Click the edit icon 🖊 that is associated with a site.
	c. Optional: Select <b>Enable Throttle</b> to manage the throughput for site replication and offload operations as described in "Editing a site" on page 250.
	d. Click <b>Save</b> .

# **Related concepts**

"Product components" on page 1

The IBM Spectrum Protect Plus solution is provided as a self-contained virtual appliance that includes storage and data movement components.

"Managing sites" on page 249

A site is an IBM Spectrum Protect Plus policy construct that is used to manage the placement of data in an environment.

# **Create backup policies**

Backup policies, which are also referred to as service level agreement (SLA) policies, define parameters that are applied to backup jobs. These parameters include the frequency and retention of backups.

#### **About this task**

The three default SLA policies are Gold, Silver, and Bronze. You can use these policies as they are or modify the policies. You can also create custom SLA policies.

If a virtual machine is associated with multiple SLA policies, ensure that the policies are not scheduled to run concurrently. Either schedule the SLA policies to run with a significant amount of time between them, or combine them into a single SLA policy.

For example purposes, this task does not include instructions for enabling replication for vSnap servers or for offloading or archiving to secondary backup storage, which are optional features. For information about how to set up these features in the SLA policy, see "Creating an SLA policy" on page 87.

Backup copies of data are called snapshots.

# **Procedure**

To create an SLA policy, complete the following steps:

- 1. In the navigation pane, click **Manage Protection > Policy Overview**.
- 2. Click Add SLA Policy.

The **New SLA Policy** pane is displayed.

- 3. In the Name field, enter a name that provides a meaningful description of the SLA policy.
- 4. In the **Operational Protection** section under **Main Policy**, set the following options for backup operations. These operations occur on the vSnap servers that are defined in the **System Configuration** > **Backup Storage** > **Disk** window.

#### Retention

Specify the retention period for the backup snapshots.

#### **Disable Schedule**

Select this check box to create the main policy without defining a frequency or start time. Policies created without a schedule can be run on-demand.

# Frequency

Enter the frequency for backup operations.

#### **Start Time**

Enter the date and time that you want the backup operation to start.

# **Target Site**

Select the target backup site for backing up data.

A site can contain one or more vSnap servers. If more than one vSnap server is in a site, IBM Spectrum Protect Plus server manages data placement in the vSnap servers.

Only sites that are associated with a vSnap server are shown in this list. Sites that are added to IBM Spectrum Protect Plus, but are not associated with a vSnap server, are not shown.

# Only use encrypted disk storage

Select this check box to back up data to encrypted vSnap servers if your environment includes a mixture of encrypted and unencrypted servers.

**Restriction:** If this option is selected and no encrypted vSnap servers are available, the associated job will fail.

The following example shows a new SLA policy named Copper that runs every 3 days at midnight with a retention of 1 month:




Figure 5. Creating an SLA policy

5. Click **Save**. The SLA policy can now be applied to backup job definitions as shown in <u>"Add resources to</u> a job definition" on page 76.

## **Related concepts**

# "Replicate backup-storage data" on page 5

When you enable replication of backup data, data from one vSnap server is asynchronously replicated to another vSnap server. For example, you can replicate backup data from a vSnap server on a primary site to a vSnap server on a secondary site.

# "Offload to secondary backup storage" on page 6

The vSnap server is the primary backup location for snapshots. All IBM Spectrum Protect Plus environments have at least one vSnap server. Optionally, you can offload snapshots from a vSnap server to secondary backup storage.

# "Manage SLA policies for backup operations" on page 87

Service level agreement (SLA) policies, also known as backup policies, define parameters for backup jobs. These parameters include the frequency and retention period of backups and the option to replicate or offload backup data. You can use predefined SLA policies, or customize them to meet your needs.

# Create a user account for the application administrator

Create a user account for an administrator who can run backup and restore operations for the hypervisors or applications that are in your environment.

## Before you begin

For example purposes, the following steps show how to create an account for an individual user who is responsible for protecting VMware data. This account uses an existing user role and resource group.

To create an account for an LDAP group, see "Creating a user account for an LDAP group" on page 283.

To create custom user roles and resource groups, see "Creating a resource group" on page 276 and "Creating a role" on page 280

## **Procedure**

To create an account for an application administrator, complete the following steps:

- 1. In the navigation pane, click **Accounts > User**.
- 2. Click Add User. The Add User pane is displayed.
- 3. Click Select the type of user or group you want to add > Individual new user.
- 4. Enter a name and password for the application administrator.
- 5. In the Assign Role section, select VM Admin.

The permissions are shown in the **Permission Groups** section.




Figure 6. Creating a user account and assigning a role

- 6. Click Continue.
- 7. In the Add Users Assign Resources section, select the All Resources resource group, and then click Add resources.

The resource group is added to the **Selected Resources** section.




Figure 7. Selecting a resource group for the user account

8. Click Create user.

# **Related concepts**

"Managing user access" on page 275

By using role-based access control, you can set the resources and permissions available to IBM Spectrum Protect Plus user accounts.

# **Add resources to protect**

Resources are servers for hypervisors or applications that host data that you want to protect. After a resource is registered, an inventory of the resource is captured and added to the IBM Spectrum Protect Plus inventory, enabling you to complete backup and restore jobs, as well as to run reports.

## **About this task**

For example purposes, this task describes how to add a VMware resource. To add other resources, see the instructions by resource type in <u>Chapter 7</u>, "Protecting hypervisors," on page 93 and <u>Chapter 8</u>, "Protecting applications," on page 129.

#### **Procedure**

To add a vCenter Server instance, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > VMware.
- 2. Click Manage vCenter, and then click Add vCenter.
- 3. Populate the fields in the **vCenter Properties** section:

# Hostname/IP

Enter the resolvable IP address or a resolvable path and machine name.

## Use existing user

Enable to select a previously entered user name and password for the vCenter Server instance.

#### Username

Enter your user name for the vCenter Server instance.

## **Password**

Enter your password for the vCenter Server instance.

#### **Port**

Enter the communications port of the vCenter Server instance. Select the **Use SSL** check box to enable an encrypted Secure Sockets Layer (SSL) connection. The typical default port is 80 for non SSL connections or 443 for SSL connections.

4. In the **Options** section, configure the following option:

# Maximum number of VMs to process concurrently per ESX server and per SLA

Set the maximum number of concurrent VM snapshots to process on the ESX server.

The following example shows populated fields.




Figure 8. Adding a vCenter Server instance

# 5. Click Save.

IBM Spectrum Protect Plus confirms a network connection, adds the resource to the database, and then catalogs the resource. If a message appears indicating that the connection is unsuccessful, review your entries. If your entries are correct and the connection is unsuccessful, contact a network administrator to verify and possible fix the connections.

# Add resources to a job definition

Before you can back up a resource, you must create a job definition that associates the resource with one or more backup policies, also referred to as SLA policies.

#### About this task

For example purposes, this task describes how select an SLA policy for resources that are in a VMware vCenter. To select a policy for other resources, see the instructions by resource type in <a href="Chapter 7">Chapter 7</a>, "Protecting hypervisors," on page 93 and Chapter 8, "Protecting applications," on page 129.

#### **Procedure**

To select an SLA policy, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > VMware.
- 2. Select the resources that you want to back up. You can select all resources in a vCenter or drill down to select specific resources.

Use the search function to search for available resources and toggle the displayed resources by using the **View** filter. Available options are **VMs and Templates**, **VMs**, **Datastore**, **Tags and Categories**, and **Hosts and Clusters**. Tags, which are applied in vSphere, make it possible assign metadata to virtual machines.

The following example shows a specific hard disk that is selected for backup:




Figure 9. Selecting resources for backup

3. Click **Select SLA Policy** to add one or more SLA policies that meet your backup data criteria to the job definition.

The following example shows the SLA policy **Copper** selected:




Figure 10. Selecting an SLA policy

- 4. To create the job definition by using default options, click **Save**.
- 5. Optional: To configure additional options, click **Select Options** and follow the instructions in <u>"Backing up VMware data"</u> on page 97.
- 6. Click Save.

After the job definition is saved, available virtual machine disks (VMDKs) in a virtual machine are discovered and are shown when **VMs and Templates** is selected in the **View** filter. By default, these VMDKs are assigned to the same SLA policy as the virtual machine. Optionally, to define a more granular policy by excluding individual VMDKs, follow the instructions in <u>"Excluding VMDKs from the SLA policy for a job" on page 101.</u>

#### Results

The job runs as defined by the SLA policies that you selected, or you can manually run the job by clicking **Jobs and Operations** and then clicking the **Policy and Job List** tab. For instructions, see <u>"Start a backup</u> job" on page 77.

## **Related concepts**

"Protecting IBM Spectrum Protect Plus" on page 227

Protect the IBM Spectrum Protect Plus application by backing up the underlying databases for disaster recovery scenarios. Configuration settings, registered resources, restore points, backup storage settings, search data, and job information are backed up to a vSnap server defined in the associated SLA policy.

# Start a backup job

You can start a backup job on demand outside of the schedule that is set by the SLA policy.

#### **Procedure**

To start a backup job on demand, complete the following steps:

- 1. In the navigation, click **Jobs and Operations**, and open the **Schedule** tab.

  If your job is not a scheduled job but is an on-demand job, click the **Job History** tab.
- 2. Choose the job that you want to run and click **Actions** > **Start** as shown in the following example:




Figure 11. Starting a job

3. To view the job log in detail, click the job in the **Running Jobs** tab.

The log screen shows the following details:

- Status: shows whether the message is an error, warning, or an information message.
- Time: shows the time stamp of the message.
- ID: shows the unique identifier for the message if applicable.
- Description: shows what the message is.
- 4. You can download a job log from the page by clicking **Download .zip**. If you want to cancel the job, click **Actions** > **Cancel**.
- 5. Click the **Actions** menu that is associated with the job that you want to start and click **Start** as shown in the following example:

# **Related concepts**

"Jobs and operations" on page 231

Use the **Jobs and Operations** window to monitor jobs, review job history, schedule jobs, view active resources, and rerun or pause jobs and schedules.

# Run a report

Run reports with predefined default parameters or custom parameters.

# **Procedure**

To run a report, complete the following steps:

- 1. In the navigation pane, click **Reports and Logs** > **Reports**.
- 2. Expand a report type and select a report to run as shown in the following example:




Figure 12. Selecting a report to run

- 3. Run the report either with custom parameters or default parameters:
  - To run the report with custom parameters, set the parameters in the **Options** section, and click **Run**. Parameters are unique to each report.
  - To run the report with default parameters, click **Run**.

# **Related concepts**

"Managing reports and logs" on page 267

IBM Spectrum Protect Plus provides a number of predefined reports that you can customize to meet your reporting requirements. A log of actions that users complete in IBM Spectrum Protect Plus is also provided.

# Chapter 5. Updating IBM Spectrum Protect Plus components

You can update the IBM Spectrum Protect Plus virtual appliance, vSnap servers, and the VADP proxy servers to get the latest features and enhancements. Software patches and updates are installed by using the IBM Spectrum Protect Plus administrative console or command-line interface for these components.

For information about available update files and how to obtain them from an IBM download site, see technote 879861.

Before you update IBM Spectrum Protect Plus components, review the hardware and software requirements for the components to confirm any changes that might have occurred from previous versions.

Review the following restrictions and tips:

- You must separately update vSnap servers that are not on IBM Spectrum Protect Plus virtual appliances.
- The update process through the administrative console updates IBM Spectrum Protect Plus features and the underlying infrastructure components including the operating system and file system. Do not use another method to update these components.
- Do not update any of the underlying components for IBM Spectrum Protect Plus unless the component
  is provided in an IBM Spectrum Protect Plus update package. Infrastructure updates are managed by
  IBM update facilities. The administrative console is the primary means for updating IBM Spectrum
  Protect Plus features and underlying infrastructure components including the operating system and file
  system.

Take the following actions:

- Before you update components, it is important that you back up your IBM Spectrum Protect Plus environment as described in "Backing up the IBM Spectrum Protect Plus application" on page 227.
- After IBM Spectrum Protect Plus is updated, it cannot roll back to a previous version without a virtual machine snapshot. Create a virtual machine snapshot of your environment before you update IBM Spectrum Protect Plus. If you later want to roll back IBM Spectrum Protect Plus to an earlier version, you must have a virtual machine snapshot. After the upgrade is completed successfully, remove the virtual machine snapshot.

# **Updating the IBM Spectrum Protect Plus virtual appliance**

Use the IBM Spectrum Protect Plus administrative console to update the virtual appliance. Updating IBM Spectrum Protect Plus can be run offline or online if you have external internet access.

# Before you begin

You can update IBM Spectrum Protect Plus V10.1.2 or later directly to the current version. If you are using V10.1.1, you must update to V10.1.2 and then update to the current version. For instructions about how to update from V10.1.1 to V10.1.2, see <u>Updating the IBM Spectrum Protect Plus virtual appliance to version 10.1.2</u>.

Before you begin the update process, complete the following steps:

1. Ensure that your IBM Spectrum Protect Plus environment is backed up before you run updates. For more information about backing up your environment, see <u>"Backing up the IBM Spectrum Protect Plus application"</u> on page 227.

- 2. For offline updates, download the prerequisite IBM Spectrum Protect Plus update named CC1QHML.iso to a directory on the computer that is running the browser for the administrative console. The update file is installed first.
- 3. Ensure that no jobs are running during the update procedure. Pause the schedule for any jobs that have a status of IDLE or COMPLETED.

For a list of download images, including the required operating system update for the virtual appliance, see technote 879861.

#### About this task

When you have access to the internet, you can choose to run the update procedure online. If you do not have access to the internet, you can run the offline update procedure.

#### **Procedure**

To update the IBM Spectrum Protect Plus virtual appliance, complete the following steps:

1. From a supported web browser, access the administrative console by entering the following address:

https://hostname:8090/

where hostname is the IP address of the virtual machine where the application is deployed.

2. In the login window, select one of the following authentication types in the **Authentication Type** list:

Authentication Type	Login information
IBM Spectrum Protect Plus	To log in as an IBM Spectrum Protect Plus user with SYSADMIN privileges, enter your administrator user name and password. If you log in by using the admin user account, you are prompted to reset the user name and password. You cannot reset the user name to admin, root, or test.
System (recommended)	To log in as a system user, enter the server admin password. The default password is sppDP758. You are prompted to change this password during the first login.

3. Click **Updates and Hotfix Management** to open the updates management page.

If you have access to the FTP site, public.dhe.ibm.com, the administrator console checks for available updates automatically and lists them.

- 4. Click **Run Update** to install the available updates.
  - When the updates are installed successfully, go to Step 6.
  - If you are planning to install an update from an ISO file, click **Click Here** to run the offline updates. Go to Step 5.

**Note:** If you want to run online updates but can see only the offline mode, check your internet connectivity and reattempt to access the FTP site, public.dhe.ibm.com.

- 5. Choose the update that you want to run, as follows:
  - Online mode: Updates are listed automatically in the repository when they are made available. Click **Run Update**.
  - Offline mode: Click **Choose file** to browse for the downloaded file. The file has an iso or rpm extension like this example, <filename>.iso. Click **Upload Update Image (or) Hotfix**.

**Note:** You can select only one update file at a time.

When the update completes, the virtual machine where the application is deployed automatically restarts.

**Important:** After the IBM Spectrum Protect Plus update completes, you must update any external vSnap and VADP proxy servers in your environment.

- 6. Clear the browser cache.
  - HTML content from previous versions of IBM Spectrum Protect Plus might be stored in the cache.
- 7. Start the updated version of IBM Spectrum Protect Plus.
- 8. In the navigation pane, click **Jobs and Operations**, and then click the **Schedule** tab. Find the jobs that you paused.
- 9. From the **Actions** menu for the paused jobs, select **Release Schedule**.

#### **Related tasks**

"Updating vSnap servers" on page 83

The default vSnap server is updated with the IBM Spectrum Protect Plus appliance. You must update additional vSnap servers that are installed on either virtual or physical appliances separately.

# **Updating vSnap servers**

The default vSnap server is updated with the IBM Spectrum Protect Plus appliance. You must update additional vSnap servers that are installed on either virtual or physical appliances separately.

# Before you begin

You can update your vSnap servers directly from version 10.1.2 or later to the current version. If you are using version 10.1.1, you must update to version 10.1.2 and then update to the current version. For instructions about how to update to version 10.1.2, see Updating vSnap servers to version 10.1.2.

Test restore jobs need to complete prior to initiating an update to vSnap. Jobs that are not completed or canceled when an upgrade is initiated will not be visible once the update has completed. If jobs are not visible once the update has completed, re-run test restore jobs.

You might also be required to update the operating system for the vSnap servers prior to updating the servers. For operating system requirements, see "Component requirements" on page 11.

To check the current version and operating system for your vSnap servers, complete the following steps:

- 1. Log on to the vSnap server as the serveradmin user. If you are using IBM Spectrum Protect Plus 10.1.1, log in by using the root account.
- 2. To check the vSnap server version and operating system, use the vSnap command-line interface to issue the following command:

```
vsnap system info
```

Ensure that no jobs that use the vSnap server are running during the update procedure. Pause the schedule for any jobs that have a status of IDLE or COMPLETED.

# Updating the operating system for a physical vSnap server

If you have installed the vSnap server on a machine that is running Red Hat Enterprise Linux, you must update the operating system to version 7.5 or 7.6 before you update the vSnap server. For instructions about how to update the operating system, see the Red Hat Enterprise Linux documentation.

# **Related tasks**

"Updating a vSnap server" on page 84

The default vSnap server is updated with the IBM Spectrum Protect Plus appliance. You must update additional vSnap servers that are installed on either virtual or physical appliances separately.

# Updating the operating system for a virtual vSnap server

If the operating system is CentOS Linux version 7.4 or earlier, you must update the operating system before you update the vSnap server. To update the operating system, follow the instructions in <u>Updating</u> vSnap servers to version 10.1.2. The version 10.1.2 installation includes CentOS Linux version 7.5.

#### Related tasks

"Updating a vSnap server" on page 84

The default vSnap server is updated with the IBM Spectrum Protect Plus appliance. You must update additional vSnap servers that are installed on either virtual or physical appliances separately.

# **Updating a vSnap server**

The default vSnap server is updated with the IBM Spectrum Protect Plus appliance. You must update additional vSnap servers that are installed on either virtual or physical appliances separately.

# Before you begin

Before you begin the update process, complete the following steps:

- 1. Ensure that you have backed up your IBM Spectrum Protect Plus environment as described in "Backing up the IBM Spectrum Protect Plus application" on page 227.
- 2. If you are updating from IBM Spectrum Protect Plus 10.1.1, you must update to version 10.1.2 and then update to the current version. For instructions about how to update to version 10.1.2, see Updating vSnap servers to version 10.1.2.
- 3. Download the vSnap update file CC1QGML.run and copy it to a temporary location on the vSnap server. For information about downloading files, see technote 879861.

#### **Procedure**

To update a vSnap server, complete the following steps:

- 1. Log on to the vSnap server as the **serveradmin** user.
- 2. From the directory where the CC1QGML.run file is located, make the file executable and run the installer by issuing the following commands:

```
chmod +x CC1QGML.run
sudo ./CC1QGML.run
```

The vSnap packages are installed.

- 3. Start the updated version of IBM Spectrum Protect Plus.
- 4. In the navigation pane, click **Jobs and Operations**, and then click the **Schedule** tab. Find the jobs that you paused.
- 5. From the **Actions** menu for the paused jobs, select **Release Schedule**.

# **Updating VADP proxies**

Updating the IBM Spectrum Protect Plus virtual appliance automatically updates all the VADP proxies that are associated with the virtual appliance. In rare scenarios such as loss of network connectivity, you must update the VADP proxy manually.

# Before you begin

Before you begin, ensure that you have backed up your IBM Spectrum Protect Plus environment as described in "Backing up the IBM Spectrum Protect Plus application" on page 227.

#### **Procedure**

If a VADP proxy update is available for external proxies during a restart of the IBM Spectrum Protect Plus virtual appliance, the update will be automatically applied to any VADP proxy associated with an identity. To associate a VADP proxy with an identity, navigate to **System Configuration** > **VADP Proxy**. Click the

options icon \*\*\* and select **Set Options**. Through the User setting, select a previously entered username and password for the VADP proxy server.

To update a VADP proxy manually, complete the following steps:

- 1. Navigate to the **System Configuration** > **VADP Proxy** page in IBM Spectrum Protect Plus.
- 2. The **VADP Proxy** page displays each proxy server. If a newer version of the VADP proxy software is available, an update icon odisplays in the **Status** field.
- 3. Ensure that there are no active jobs that use the proxy, and then click the update icon .

  The proxy server enters a suspended state and installs the latest update. When the update completes, the VADP proxy server automatically resumes and enters an enabled state.

If you are attempting to update as a non-root user, special instructions will need to be followed in order to push-install or push-update a VADP proxy.

1. Create a file in the /etc/sudoers.d/ directory.

```
sudo cd /etc/sudoers.d/
```

2. Write the text to the file and save it by pressing CTRL+D on the keyboard when done.

```
sudo cat > 99-vadpuser
    Defaults !requiretty
    vadpuser ALL=NOPASSWD: /tmp/cdm_guestapps_vadpuser/runcommand.sh
<<Press CTRL+D>>
```

3. Set the appropriate permissions on the file.

```
sudo chmod 0440 99-vadpuser
```

#### What to do next

After you update the VADP proxies, complete the following action:

Action	How to
Run the VMware backup job.	See "Backing up VMware data" on page 97.
	The proxies are indicated in the job log by a log message similar to the following text:
	Run remote vmdkbackup of MicroService: http:// <pre>http://<pre></pre></pre>
	nodename, IP:proxy_IP_address

## **Related tasks**

"Creating VADP proxies" on page 103

You can create VADP proxies to run VMware backup jobs with IBM Spectrum Protect Plus in Linux environments.

#### **Related reference**

"Editing firewall ports" on page 47

Use the provided examples as a reference for opening firewall ports on remote VADP proxy servers or application servers. You must restrict port traffic to only the required network or adapters.

# **Applying early availability updates**

Early availability updates provide fixes for authorized program analysis reports (APARs) and minor issues between IBM Spectrum Protect Plus releases. These updates are available in bundles from the Fix Central Online website.

#### About this task

Early availability updates might not contain fixes for all IBM Spectrum Protect Plus components.

For instructions about how to obtain and install interim fixes, see the download information that is published when the fixes are available.

# Chapter 6. Manage SLA policies for backup operations

Service level agreement (SLA) policies, also known as backup policies, define parameters for backup jobs. These parameters include the frequency and retention period of backups and the option to replicate or offload backup data. You can use predefined SLA policies, or customize them to meet your needs.

The following default SLA policies are available. Each policy specifies a frequency and retention period for the backup. You can use these policies as they are or modify them. You can also create custom SLA policies.

#### Gold

This policy runs every 4 hours with a retention period of 1 week.

#### Silver

This policy runs daily with a retention period of 1 month.

#### **Bronze**

This policy runs daily with a retention period of 1 week.

To view and manage backup policies and to monitor the virtual machines and databases that are protected by policies, click **Manage Protection** > **Policy Overview** in the navigation pane.

If you edit an existing SLA policy by changing the cloud offload source, offload destination type, or target offload server options, associated jobs will start a full base backup, not an incremental backup, during the next job run.

For installations of IBM Spectrum Protect Plus V10.1.4, a demo SLA configuration is available for testing. This demonstration feature includes the following elements:

- · A demonstration site named **Demo**
- An SLA policy named **Demo**
- A local vSnap configuration for the demo SLA.

You can choose to use the demo site for testing backup and restore operations. The data is backed up to the local vSnap configuration when you run the demo SLA policy.

**Note:** The built-in vSnap is set so that it can be used only by the Demo Site. Do not use the built-in IBM Spectrum Protect Plus vSnap with any other site.

# Creating an SLA policy

You can create custom SLA policies to define backup frequency, retention, replication, and offload policies that are specific for your environment.

# **About this task**

If a virtual machine is associated with multiple SLA policies, ensure that the policies that you create are not scheduled to run concurrently. Either schedule the SLA policies to run with a significant amount of time between them, or combine them into a single SLA policy.

If a snapshot replication task is started before an initial backup to a vSnap server is completed, errors in the job log indicate that no recovery points exist for the database. After the initial backup to the vSnap server is completed, run the replication task again to replicate the snapshots as configured in the SLA policy.

#### **Procedure**

To create an SLA policy, complete the following steps:

- 1. In the navigation pane, click **Manage Protection** > **Policy Overview**.
- 2. Click Add SLA Policy.

The **New SLA Policy** pane is displayed.

- 3. In the Name field, enter a name that provides a meaningful description of the SLA policy.
- 4. In the **Operational Protection** section under **Main Policy**, set the following options for backup operations. These operations occur on the vSnap servers that are defined in the **System Configuration** > **Backup Storage** > **Disk** window.

#### Retention

Specify the retention period for the backup snapshots.

#### **Disable Schedule**

Select this check box to create the main policy without defining a frequency or start time. Policies created without a schedule can be run on-demand.

# Frequency

Enter a frequency for backup operations.

#### **Start Time**

Enter the date and time that you want the backup operation to start.

# **Target Site**

Select the target backup site for backing up data.

A site can contain one or more vSnap servers. If more than one vSnap server is in a site, IBM Spectrum Protect Plus server manages data placement in the vSnap servers.

Only sites that are associated with a vSnap server are shown in this list. Sites that are added to IBM Spectrum Protect Plus, but are not associated with a vSnap server, are not shown.

# Only use encrypted disk storage

Select this check box to back up data to encrypted vSnap servers if your environment includes a mixture of encrypted and unencrypted servers.

**Restriction:** If this option is selected and there are no encrypted vSnap servers available, the associated job will fail.

5. Under **Replication Policy**, set the following options to enable asynchronous replication from one vSnap server to another. For example, you can replicate data from the primary to the secondary backup site.

**Replication partnerships requirement:** These options apply to established replication partnerships. To add a replication partnership, see the instructions in <u>"Establishing a replication partnership for a vSnap server"</u> on page 59.

## **Backup Storage Replication**

Select this option to enable replication.

#### Disable Schedule

Select this check box to create the replication relationship without defining a frequency or start time.

# Frequency

Enter a frequency for replication operations.

#### **Start Time**

Enter the date and time that you want the replication operation to start.

## **Target Site**

Select the target backup site for replicating data.

A site can contain one or more vSnap servers. If more than one vSnap server is in a site, IBM Spectrum Protect Plus server manages data placement in the vSnap servers.

Only sites that are associated with a vSnap server are shown in this list. Sites that are added to IBM Spectrum Protect Plus, but are not associated with a vSnap server, are not shown.

# Only use encrypted disk storage

Select this option to replicate data to encrypted vSnap servers if your environment includes a mixture of encrypted and unencrypted servers.

**Restriction:** If this option is selected and there are no encrypted vSnap servers available, the associated job will fail.

#### Same retention as source selection

Select this option to use the same retention policy as the source vSnap server. To set a different retention policy, clear this option and set a different policy.

6. In the Additional Protection section, set the following options to offload and archive data.

**Tip:** When you specify Additional Protection, you are choosing to create a copy.

#### Cloud

Select this option to offload data to cloud storage or to a repository server.

**Important:** By clicking **Additional Protection** > **Cloud**, you create an incremental copy of data to a cloud storage system or to an IBM Spectrum Protect server.

Data is backed up to the vSnap server for short term protection, and then offloaded to the selected cloud storage or repository server for longer-term protection. During the first offload of a backup volume, the snapshot is backed up in full. After the first offload of the base snapshot is completed, subsequent offloads are incremental and capture cumulative changes since the last offload. Cloud or repository server restore operations can be performed from any available vSnap server.

# **Disable Schedule**

Select this check box to create the offload relationship without defining a frequency or start time

# Frequency

Enter a frequency for offload operations.

#### **Start Time**

Enter the date and time that you want the offload operation to start.

# Same retention as source selection

Select this option to use the same retention policy for the cloud offload backup as the source vSnap server. To set a different retention policy, clear this option and set a different policy.

**Restriction:** Offload retention options are disabled if a server that uses write once read many (WORM) retention is selected in the **Target Offload Server** field.

#### Source

ı

Click the source for the offload operation:

#### **Main Policy Destination**

The source for the offload operation is the target site that is defined in the **Main Policy** section.

# **Replication Policy Destination**

The source for the offload operation is the target site that is defined in the **Replication Policy** section.

This option is available only when **Backup Storage Replication** is selected.

#### **Destination**

Click Cloud Servers or Repository Servers.

#### **Target**

Click the cloud storage system or repository server to which you want to offload data.

This list contains the secondary storage systems that you have added to IBM Spectrum Protect Plus. If you have not added secondary storage or want to add it, see "Managing secondary backup storage" on page 237 for information about the cloud storage systems and repository servers that are supported and how to add them to IBM Spectrum Protect Plus.

#### **Archive**

Select this option to archive data to cloud storage or to a repository server for long-term protection.

**Important:** By clicking **Additional Protection** > **Archive**, you create a full copy of data to a cloud storage system or to tape by using an IBM Spectrum Protect server.

This operation provides a full image offload to the selected archival storage.

#### **Disable Schedule**

Select this check box to create the archive relationship without defining a frequency or start time.

# **Frequency**

Enter a frequency for archive operations.

#### **Start Time**

Enter the date and time that you want the archive operation to start.

#### Retention

Specify the retention period for the archive snapshots as a unit of time in days, months, or years.

# **Source**

Click the source for the archive destination:

# **Main Policy Destination**

The source for the archive operation is the target site that is defined in the **Main Policy** section.

# **Replication Policy Destination**

The source for the archive operation is the target site that is defined in the **Replication Policy** section.

This option is available only when **Backup Storage Replication** is selected.

# **Destination**

Click Cloud Servers or Repository Servers.

#### **Target**

Click the cloud storage system or repository server to which you want to archive data.

Only cloud targets that have a defined archive bucket are shown in this list. To add an archive bucket for a cloud storage system, follow the instructions in "Managing cloud storage" on page 237.

7. Click **Save**. The SLA policy can now be applied to backup job definitions.

#### What to do next

After you create an SLA policy, complete the following actions:

Action	How to
Assign user permissions to the SLA policy.	See <u>"Creating a role" on page 280</u>
Create a backup job definition that uses the SLA policy.	See the backup topics in Chapter 7, "Protecting hypervisors," on page 93 and Chapter 8, "Protecting applications," on page 129.

## **Related concepts**

"Replicate backup-storage data" on page 5

When you enable replication of backup data, data from one vSnap server is asynchronously replicated to another vSnap server. For example, you can replicate backup data from a vSnap server on a primary site to a vSnap server on a secondary site.

"Offload to secondary backup storage" on page 6

The vSnap server is the primary backup location for snapshots. All IBM Spectrum Protect Plus environments have at least one vSnap server. Optionally, you can offload snapshots from a vSnap server to secondary backup storage.

# **Editing an SLA policy**

Edit the options for an SLA policy to reflect changes in your IBM Spectrum Protect Plus environment.

# **Procedure**

To edit an SLA policy, complete the following steps:

- 1. In the navigation pane, click **Manage Protection > Policy Overview**.
- 2. Click the edit icon / that is associated with a policy.
  The **Edit SLA Policy** pane is displayed.
- 3. Edit the policy options, and then click Save.

# **Deleting an SLA policy**

Delete an SLA policy when it becomes obsolete.

# Before you begin

Ensure that there are no jobs that are associated with the SLA policy.

#### **Procedure**

To delete an SLA policy, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Policy Overview.
- 2. Click the delete icon  $\times$  that is associated with an SLA policy.
- 3. Click **Yes** to delete the policy.
- 4. If you are deleting the demo SLA policy, go to **System Configuration** > **Site**, and delete the site named Demo.

#### Note:

When you delete the demo site you must register the local host vSnap with user credentials to another valid site.

# **Chapter 7. Protecting hypervisors**

You must register the hypervisors that you want to protect in IBM Spectrum Protect Plus and then create jobs to back up and restore the virtual machines and resources that are associated with the hypervisors.

# **Backing up and restoring VMware data**

To protect VMware data, first add vCenter Server instances in IBM Spectrum Protect Plus, and then create jobs for backup and restore operations for the content of the instances.

# **System requirements**

Ensure that your VMware environment meets the system requirements in <u>"Hypervisor requirements" on page 21.</u>

# **Support for VMware tags**

IBM Spectrum Protect Plus supports VMware virtual machine tags. Tags are applied in vSphere and allow users to assign metadata to virtual machines. When applied in vSphere and added to the IBM Spectrum Protect Plus inventory, virtual machine tags can be viewed through the **View** > **Tags & Categories** filter when you create a job definition. For more information about VMware tagging, see Tagging Objects.

# **Support for encryption**

Backing up and restoring encrypted virtual machines is supported in vSphere 6.5 environments and later. Encrypted virtual machines can be backed up and restored at the virtual machine-level to their original location. If you are restoring to an alternate location, the encrypted virtual machine is restored without encryption, and must be encrypted manually through vCenter Server after the restore completes.

The following vCenter Server privileges are required to enable operations for encrypted virtual machines:

- Cryptographer.Access
- Cryptographer.AddDisk
- Cryptographer.Clone

**Note:** An NFS volume may be mounted to any number of datacenters that belong to the same vCenter. If an NFS volume is mounted on more than one datacenter, vCenter treats the same volume as two different datastores. IBM Spectrum Protect Plus treats this as a single datastore and combines all of the VMs and VMDKs residing on the datastore from all of the datacenters on which the datastore is mounted. Any SLA selection against this datastore will cause all of the VMs from the different datacenters to be backed up or restored in IBM Spectrum Protect Plus.

# **Adding a vCenter Server instance**

When a vCenter Server instance is added to IBM Spectrum Protect Plus, an inventory of the instance is captured, enabling you to complete backup and restore jobs, as well as run reports.

#### **Procedure**

To add a vCenter Server instance, complete the following steps:

- 1. In the navigation pane, click **Manage Protection** > **Hypervisors** > **VMware**.
  - 2. Click Manage vCenter.
  - 3. Click Add vCenter.
  - 4. Populate the fields in the vCenter Properties section:

#### Hostname/IP

Enter the resolvable IP address or a resolvable path and machine name.

# Use existing user

Enable to select a previously entered user name and password for the vCenter Server instance.

#### Username

Enter your user name for the vCenter Server instance.

#### **Password**

Enter your password for the vCenter Server instance.

#### Port

Enter the communications port of the vCenter Server instance. Select the **Use SSL** check box to enable an encrypted Secure Sockets Layer (SSL) connection. The typical default port is 80 for non SSL connections or 443 for SSL connections.

5. In the **Options** section, configure the following option:

# Maximum number of VMs to process concurrently per ESX server and per SLA

Set the maximum number of concurrent VM snapshots to process on the ESX server.

6. Click **Save**. IBM Spectrum Protect Plus confirms a network connection, adds the vCenter Server instance to the database, and then catalogs the instance.

If a message appears indicating that the connection is unsuccessful, review your entries. If your entries are correct and the connection is unsuccessful, contact a network administrator to review the connections.

#### What to do next

After you add a vCenter Server instance, complete the following action:

Action	How to
Assign user permissions to the hypervisor.	See <u>"Creating a role" on page 280</u> .

## **Related concepts**

"Managing identities" on page 285

Some features in IBM Spectrum Protect Plus require credentials to access your resources. For example, IBM Spectrum Protect Plus connects to Oracle servers as the local operating system user that is specified during registration to complete tasks like cataloging, data protection, and data restore.

# **Related tasks**

"Backing up VMware data" on page 97

Use a backup job to back up VMware resources such as virtual machines, datastores, folders, vApps, and datacenters with snapshots.

# "Restoring VMware data" on page 106

VMware restore jobs support Instant VM Restore and Instant Disk Restore scenarios, which are created automatically based on the selected source.

# Virtual machine privileges

vCenter Server privileges are required for the virtual machines that are associated with a VMware provider. These privileges are included in the vCenter Administrator role.

If the user that is associated with the provider is not assigned to the Administrator role for an inventory object, the user must be assigned to a role that has the following required privileges. Ensure that the privileges are propagated to child objects. For instructions, refer to the VMware documentation about adding a permission to an inventory object.

vCenter Server Object	Required Privileges
Alarm	Acknowledge alarm     Set alarm status

vCenter Server Object	Required Privileges
Cryptographic Operations (6.5 and 6.7)	<ul> <li>Add disk</li> <li>Direct access</li> <li>Encrypt</li> <li>Encrypt new</li> <li>Manage encryption policies</li> </ul>
Datastore	<ul> <li>Allocate space</li> <li>Browse datastore</li> <li>Low level file operations</li> <li>Remove datastore</li> <li>Remove file</li> <li>Update virtual machine files</li> </ul>
Distributed switch	<ul><li>Port configuration operation</li><li>Port setting operation</li></ul>
Folder	Create folder
Global	Cancel task
Host > Configuration	Storage partition configuration
Inventory Service > Tagging (6.0) vSphere Tagging (6.5 and 6.7)	<ul> <li>Assign or Unassign vSphere Tag</li> <li>Create vSphere Tag</li> <li>Create vSphere Tag Category</li> <li>Modify UsedBy Field for Category</li> <li>Modify UsedBy Field for Tag</li> </ul>
Network	Assign network
Resource	<ul> <li>Apply recommendation</li> <li>Assign a vApp to resource pool</li> <li>Assign virtual machine to resource pool</li> <li>Migrate powered off virtual machine</li> <li>Migrate powered on virtual machine</li> <li>Query vMotion</li> </ul>

vCenter Server Object	Required Privileges
Virtual Machine > Configuration	<ul> <li>Add existing disk</li> <li>Add new disk</li> <li>Add or remove device</li> <li>Advanced (6.0 and 6.5)</li> <li>Advanced configuration (6.7)</li> <li>Change CPU count</li> <li>Change memory (6.7)</li> <li>Configure raw device (6.7)</li> <li>Disk change tracking (6.0 and 6.5)</li> <li>Memory (6.0 and 6.5)</li> <li>Modify device settings</li> <li>Raw device (6.0 and 6.5)</li> <li>Reload from path</li> <li>Remove disk</li> <li>Rename</li> <li>Settings</li> <li>Toggle disk change tracking (6.7)</li> </ul>
Virtual Machine > Guest Operations	<ul><li>Guest Operation Modifications</li><li>Guest Operation Program Execution</li><li>Guest Operation Queries</li></ul>
Virtual Machine > Interaction	Backup operation on virtual machine     Power Off     Power On
Virtual Machine > Inventory	<ul><li>Register</li><li>Remove</li><li>Unregister</li></ul>
Virtual Machine > Provisioning	<ul> <li>Allow disk access</li> <li>Allow read-only disk access</li> <li>Allow virtual machine download</li> <li>Allow virtual machine files upload</li> <li>Mark as template</li> <li>Mark as virtual machine</li> </ul>
Virtual Machine > Snapshot management	<ul><li> Create snapshot</li><li> Remove snapshot</li><li> Revert snapshot</li></ul>

vCenter Server Object	Required Privileges
vApp	Add virtual machine
	Assign resource pool
	Assign vApp
	• Create
	• Delete
	Power Off
	Power On
	• Rename
	Unregister
	vApp resource configuration

### **Detecting VMware resources**

VMware resources are automatically detected after the vCenter Server instance is added to IBM Spectrum Protect Plus. However, you can run an inventory job to detect any changes that occurred since the instance was added.

### **Procedure**

To run an inventory job, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > VMware.
- 2. In the list of vCenters Server instances, select an instance or click the link for the instance to navigate to the resource that you want. For example, if you want to run an inventory job for an individual virtual machine in the instance, click the instance link and then select a virtual machine.
- 3. Click Run Inventory.

### Testing the connection to a vCenter Server virtual machine

You can test the connection to a vCenter Server virtual machine. The test function verifies communication with the virtual machine and tests domain name server (DNS) settings between the IBM Spectrum Protect virtual appliance and the virtual machine.

#### **Procedure**

To test the connection, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > VMware.
- 2. In the list of vCenters Server instances, click the link for a vCenter Server to navigate to the individual virtual machines.
- 3. Select a virtual machine, and then click **Select Options**.
- 4. Select Use existing user.
- 5. Select a user in the **Select user** list.
- 6. Click **Test**.

### **Backing up VMware data**

Use a backup job to back up VMware resources such as virtual machines, datastores, folders, vApps, and datacenters with snapshots.

### Before you begin

Review the following procedures and considerations before you create a backup job definition:

• Register the providers that you want to back up. For more instructions, see <u>"Adding a vCenter Server instance"</u> on page 93.

- Configure SLA policies. For more instructions, see "Create backup policies" on page 70.
- Before an IBM Spectrum Protect Plus user can implement backup and restore operations, roles must be
  assigned to the user. Grant users access to hypervisors and backup and restore operations by using the
  Accounts pane. Roles and associated permissions are assigned during user account creation. For more
  information, see Chapter 13, "Managing user access," on page 275 and "Managing user accounts" on
  page 283.
- If a virtual machine is associated with multiple SLA policies, ensure that the policies are not scheduled to run concurrently. Either schedule the SLA policies to run with a significant amount of time between them, or combine them into a single SLA policy.
- If your vCenter is a virtual machine, to help maximize data protection, have the vCenter on a dedicated datastore and backed up in a separate backup job.
- When backing up VMware virtual machines, IBM Spectrum Protect Plus downloads .vmx, .vmxf, and .nvram files if necessary, and then it transfers those files to the vSnap as needed. For this to work successfully, the IBM Spectrum Protect Plus appliance must be able to resolve and access all protected ESXi hosts; and when communicating with an ESXi host, the correct IP address must be returned.
- If a VM is protected by an SLA policy, the backups of the VM will be retained based on the retention parameters of the SLA policy, even if the VM is removed from vCenter.
- In some cases, VMware backup jobs fail with "failed to mount" errors. To resolve this issue, increase the maximum number of NFS mounts to at least 64 by using the NFS.MaxVolumes (vSphere 5.5 and later) and NFS41.MaxVolumes (vSphere 6.0 and later) values. Follow the instructions in <a href="Increasing the default value that defines the maximum number of NFS mounts on an ESXi/ESX host">Increasing the default value that defines the maximum number of NFS mounts on an ESXi/ESX host.</a>
- If an existing VM is vMotioned, IBM Spectrum Protect Plus will perform a rebase if necessary.
- Ensure the latest version of VMware Tools is installed on VMware virtual machines.

**Restriction:** File cataloging, backup, point-in-time restores, and other operations that invoke the Windows agent will fail if a non-default local administrator is entered as the **Guest OS Username** when defining a backup job. A non-default local administrator is any user that has been created in the guest OS and has been granted the administrator role.

This occurs if the registry key LocalAccountTokenFilterPolicy in [HKLM\SOFTWARE\Microsoft \Windows\CurrentVersion\Policies\System] is set to 0 or not set. If the parameter is set to 0 or not set, a local non-default administrator cannot interact with WinRM, which is the protocol IBM Spectrum Protect Plus uses to install the Windows agent for file cataloging, send commands to this agent, and get results from it.

Set the LocalAccountTokenFilterPolicy registry key to 1 on the Windows guest that is being backed up with Catalog File Metadata enabled. If the key does not exist, navigate to [HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Policies\System] and add a DWord Registry key named LocalAccountTokenFilterPolicy with a value of 1.

### **Procedure**

To define a VMware backup job, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > VMware.
- 2. Select resources to back up.
  - Use the search function to search for available resources and toggle the displayed resources by using the **View** filter. Available options are **VMs and Templates**, **VMs**, **Datastore**, **Tags and Categories**, and **Hosts and Clusters**. Tags are applied in vSphere, and allow a user to assign metadata to virtual machines.
- 3. Click **Select SLA Policy** to add one or more SLA policies that meet your backup data criteria to the job definition.
- 4. To create the job definition by using default options, click **Save**.
  - The job runs as defined by the SLA policies that you selected. To run the job manually, click **Jobs and Operations** > **Schedule**. Select the job and click **Actions** > **Start**.

**Tip**: The **Run**button is only enabled for a single hypervisor backup, and the hypervisor must have an SLA policy applied.

When the job definition is saved, available virtual machine disks (VMDKs) in a virtual machine are discovered and are shown when **VMs and Templates** is selected in the **View** filter. By default, these VMDKs are assigned to the same SLA policy as the virtual machine. If you want a more granular backup operation, you can exclude individual VMDKs from the SLA policy. For instructions, see "Excluding VMDKs from the SLA policy for a job" on page 101.

5. To edit options before you create the job definition, click **Select Options**.

In the **Backup Options** section, set the following job definition options:

### **Skip Read-only datastores**

Skip datastores that are mounted as read-only.

### **Skip temporary datastores mounted for Instant Access**

Exclude temporary Instant Access datastores from the backup job definition.

### **VADP Proxy**

Select a VADP proxy to balance the load.

### **Priority**

Set the backup priority of the selected resource. Resources with a higher priority setting are backed up first in the job. Click the resource that you want to prioritize in the **VMware Backup** section, and then set the backup priority in the **Priority** field. Set 1 for the highest priority resource or 10 for the lowest. When a priority value is not set, automatically assigns a priority of 5 is set by default.

In the **Snapshot Options** section, set the following job definition options:

### Make VM snapshot application/file system consistent

Enable this option to turn on application or filesystem consistency for the virtual machine snapshot. All VSS-compliant applications such as Microsoft Active Directory, Microsoft Exchange, Microsoft SharePoint, Microsoft SQL, and the system state are quiesced. VMDKs and virtual machines can be instantly mounted to restore data that is related to quiesced applications.

### VM Snapshot retry attempts

Set the number of times that IBM Spectrum Protect Plus attempts to capture an application or file-consistent snapshot of a virtual machine before the job is canceled. If the **Fall back to unquiesced snapshot if quiesced snapshot fails** option is enabled, an unquiesced snapshot will be taken after the retry attempts.

### Fall back to unquiesced snapshot if quiesced snapshot fails

Enable to fall back to a non-application or non-file-system consistent snapshot if the application consistent snapshot fails. Selecting this option ensures that an unquiesced snapshot is taken if environmental issues prohibit the capture of an application or file-system consistent snapshot.

In the **Agent Options** section, set the following job definition options:

### **Truncate SQL logs**

To truncate application logs for SQL Server during the backup job, enable the **Truncate SQL logs** option. The credentials must be established for the associated virtual machine by using the Guest OS user name and Guest OS Password option within the backup job definition. When the virtual machine is attached to a domain, the user identity follows the default *domain*\name format. If the user is a local administrator, the format <code>local\_administrator</code> is used.

The user identity must have local administrator privileges. On the SQL Server server, the system login credential must have the following permissions:

- SQL Server sysadmin permissions must be enabled.
- The **Log on as a service** right must be set. For more information about this right, see <u>Add the Log on</u> as a service Right to an Account.

IBM Spectrum Protect Plus generates log files for the log truncation function and copies them to the following location on the IBM Spectrum Protect appliance:

/data/log/guestdeployer/latest\_date/latest\_entry/vm\_name

Where *latest\_date* is the date that the backup job and log truncation occurred, *latest\_entry* is the universally unique identifier (UUID) for the job, and *vm\_name* is the hostname or IP address of the VM where the log truncation occurred.

**Restriction:** File indexing and file restore are not supported from restore points that were offloaded to cloud resources or repository servers.

### Catalog file metadata

Turn on file indexing for the associated snapshot. When file indexing is completed, individual files can be restored by using the **File Restore** pane in IBM Spectrum Protect Plus. Credentials must be established for the associated virtual machine by using an SSH key, or a **Guest OS Username** and **Guest OS Password** options within the backup job definition. Ensure that the virtual machine can be accessed from the IBM Spectrum Protect Plus appliance either by using DNS or a host name.

Restrictions: SSH Keys are not valid authorization mechanism for Windows platforms.

File indexing and file restore are not supported from restore points that were offloaded to cloud resources or repository servers.

### **Exclude Files**

Enter directories to skip when file indexing is performed. Files within these directories are not added to the IBM Spectrum Protect Plus catalog and are not available for file recovery. Directories can be excluded through an exact match or with wildcard asterisks specified before the pattern (\*test) or after the pattern (test\*). Multiple asterisk wildcards are also supported in a single pattern. Patterns support standard alphanumeric characters as well as the following special characters: - \_ and \*. Separate multiple filters with a semicolon.

#### Use existing user

Select a previously entered user name and password for the provider.

### **Guest OS Username/Password**

For some tasks (such as cataloging file metadata, file restore, and IP reconfiguration), credentials must be established for the associated virtual machine. Enter the user name and password, and ensure that the virtual machine can be accessed from the IBM Spectrum Protect Plus appliance either by using DNS or a host name.

6. To troubleshoot a connection to a hypervisor virtual machine, use the **Test** function.

The **Test** function verifies communication with the virtual machine and tests DNS settings between the IBM Spectrum Protect Plus appliance and the virtual machine. To test a connection, select a single virtual machine, then click **Select Options**. Select **Use existing user** and select a previously entered user name and password for the resource. The **Test** button displays to the right of the **Save** button in the **Options** section. Click **Test**.

- 7. Click Save.
- 8. To configure additional options, click the **Policy Options** field that is associated with the job in the **SLA Policy Status** section. Set the additional policy options:

### **Pre-scripts and Post-scripts**

Run a pre-script or a post-script. Pre-scripts and post-scripts are scripts that can be run before or after a job runs. Windows-based machines support Batch and PowerShell scripts while Linux-based machines support shell scripts.

In the **Pre-script** or **Post-script** section, select an uploaded script and a script server where the script will run. Scripts and script servers are configured by using the **System Configuration** > **Script** page.

To continue running the job if the script associated with the job fails, select **Continue job/task on script error**.

When this option is enabled, if a pre-script or post-script completes processing with a non-zero return code, the backup or restore operation is attempted and the pre-script task status is reported as COMPLETED. If a post-script completes with a non-zero return code, the post-script task status is reported as COMPLETED.

When this option is disabled, the backup or restore is not attempted, and the pre-script or post-script task status is reported as FAILED.

### Run inventory before backup

Run an inventory job and capture the latest data of the selected resources before starting the backup job.

### **Exclude Resources**

Exclude specific resources from the backup job by using single or multiple exclusion patterns. Resources can be excluded by using an exact match or with wildcard asterisks specified before the pattern (\*test) or after the pattern (test\*).

Multiple asterisk wildcards are also supported in a single pattern. Patterns support standard alphanumeric characters as well as the following special characters: - \_ and \*.

Separate multiple filters with a semicolon.

### Force Full Backup of Resources

Force base backup operations for specific virtual machines or databases in the backup job definition. Separate multiple resources with a semicolon.

9. To save any additional options that you configured, click Save.

#### What to do next

After you define a backup job, you can complete the following actions:

Action	How to
If you are using a Linux environment, consider creating VADP proxies to enable load sharing.	See "Creating VADP proxies" on page 103.
Create a VMware restore job definition.	See <u>"Restoring VMware data" on page 106</u> .

### Related concepts

"Configuring scripts for backup and restore operations" on page 234

Prescripts and postscripts are scripts that can be run before or after backup and restore jobs run at the job level. Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts are created locally, uploaded to your environment through the **Script** page, and then applied to job definitions.

### **Related tasks**

"Starting jobs" on page 232

You can run any job on demand, even if the job is set to run on a schedule.

### **Excluding VMDKs from the SLA policy for a job**

After you save a backup job definition, you can exclude individual VMDKs in a virtual machine from the SLA policy that is assigned to job.

### Before you begin

Excluding one or more VMDKs from a backup operation can impact the success of recovery. Consider the following scenarios before excluding a disk from a VM backup operation.

• For Instant Disk Restore, if a VMDK is selected for a restore operations, an existing VM is chosen as the destination. IBM Spectrum Protect Plus mounts the restored disk to the chosen destination VM.

- For Instant VM Restore, if the VMDK that was excluded during a backup contains data that is necessary to boot the virtual machine, then the restored VM may fail to boot.
- For VMs with Windows-based guests, the restored VM may fail to boot if the disk on which the main operating system is installed, typically the C: drive, was excluded during the backup operation.
- For VMs with Linux-based guests, the restored VM may fail:
  - If a disk containing the boot or root partition was excluded during backup.
  - If a disk containing a data (non-root) partition was excluded during backup, and the data volume did not have the 'nofail' option specified in /etc/fstab, then the restored VM may fail.

#### **Procedure**

To exclude VMDKs from the SLA policy:

- 1. In the navigation pane, click Manage Protection > Hypervisors > VMware.
- 2. Select VMs and Templates in the View filter.
- 3. Click the link for the vCenter, and then click the link for the virtual machine that contains the VMDKs that you want to exclude.
- 4. Select one or more VMDKs, and then click **Select SLA Policy**.
- 5. Clear the check box for the selected SLA policy, and then click **Save**.

### **Backing up a Linux-based vCenter Server Appliance**

To back up a Linux-based vCenter Server Appliance, you must modify the VMware pre-freeze and post-thaw scripts on the vCenter virtual machine to avoid corrupted vCenter backups.

#### **Procedure**

To modify the scripts, complete the following steps:

1. On the virtual machine, navigate to the /usr/sbin directory and replace the content of the pre-freeze-script script with the following content:

2. Replace the content of the post-thaw-script script with the following content:

```
#!/bin/bash
#set log directory
log="/var/log/ypostgres_backup.log"
#set and log start date
today='date +%Y\/\%m\/\%d\ \%H:\%M:\%S'
echo "$\{\text{today}\}: Release of backup" >> \{\text{log}\}
#execute release command
cmd='echo \"SELECT pg_stop_backup();\" | sudo /opt/vmware/vpostgres/9.4/bin/psql -U postgres >> \{\text{log}\} 2>&1"
eval \{\text{cmd}\}
#set and log end date
today='date +\%Y\/\%m\/\%d\ \%H:\%M:\%S'
echo "\{\text{today}\}: Finished thaw script" >> \{\text{log}\}
```

# Managing VADP backup proxies

In IBM Spectrum Protect Plus, you can create proxies to run VMware backup jobs by using vStorage API for Data Protection (VADP) in Linux environments. The proxies reduce demand on system resources by enabling load sharing and load balancing. Throttling ensures that multiple VADP proxies are optimally utilized to maximize data throughput. For each virtual machine being backed up, IBM Spectrum Protect Plus determines which VADP proxy is the least busy and has the most available memory and free tasks. Free tasks are determined by the number of available CPU cores or by using the **Softcap task limit** option.

Ensure that you have the required user permissions to work with VADP proxies. For instructions about managing VADP proxy permissions, see "Permission types" on page 281.

The backup of a VMware virtual machine includes the following files:

- VMDKs corresponding to all disks. The base backup captures all allocated data, or all data if disks are
  on NFS datastores. Incremental backups will capture only changed blocks since the last successful
  backup.
- Virtual machine templates
- VMware files with the following extensions:
  - .vmx
  - .vmfx (if available)
  - .nvram (stores the state of the virtual machine BIOS)

If proxies exist, the entire processing load is shifted off the host system and onto the proxies. If proxies do not exist, the entire load stays on the host. Throttling ensures that multiple VADP proxies are optimally utilized to maximize data throughput. For each virtual machine being backed up, IBM Spectrum Protect Plus determines which VADP proxy is the least busy and has the most available memory and free tasks.

If a proxy server goes down or is otherwise unavailable before the start of the job, the other proxies take over and the job is complete. If no other proxies exist, the host takes over the job. If a proxy server becomes unavailable when a job is running, the job might fail.

Transport modes describe the method by which a VADP proxy moves data. The transport mode is set as a property of the proxy. Most backup and recovery jobs are later configured to use one or more proxies.

VADP proxies in IBM Spectrum Protect Plus support the following VMware transport modes: SAN, HotAdd, NBDSSL, and NBD.

Although every enterprise differs, and priorities in terms of size, speed, reliability, and complexity vary from environment to environment, the following general guidelines apply to the Transport Mode selection:

- SAN transport mode should be used in a direct storage environment because this mode is fast and generally reliable.
- HotAdd transport mode should be used if the VADP proxy is virtualized. This mode supports all vSphere storage types.
- NBD or NBDSSL transport mode (LAN) is the fallback mode because it works in physical, virtual, and
  mixed environments. However, with this mode, data transfer speed might be compromised if network
  connections are slow. NBDSSL mode is similar to NBD mode except that data transferred between the
  VADP proxy and the ESXi server is encrypted when using NBDSSL.

### **Creating VADP proxies**

You can create VADP proxies to run VMware backup jobs with IBM Spectrum Protect Plus in Linux environments.

### Before you begin

Note the following considerations before creating VADP proxies:

- Review the IBM Spectrum Protect Plus system requirements in "VADP proxy requirements" on page 16.
- The IBM Spectrum Protect Plus version of the VADP proxy installer includes Virtual Disk Development Kit (VDDK) version 6.5. This version of the VADP proxy installer provides the external VADP proxy support with vSphere 6.5.

#### **Procedure**

To create VMware VADP proxies, complete the following steps:

1. In the navigation pane, click **System Configuration** > **VADP Proxy**.

- 2. Click Register Proxy.
- 3. Complete the following fields in the **Install VADP Proxy** pane:

### Hostname/IP

Enter the resolvable IP address or a resolvable path and machine name.

#### Select a site

Select a site to associate with the proxy.

### Use existing user

Enable to select a previously entered username and password for the provider.

#### Username

Enter the user name for the VADP proxy server.

#### **Password**

Enter the password name for the VADP proxy server.

### 4. Click Install.

The proxy is added to the **VADP Proxy** table.

5. Click **Register** to register the proxy server.

You can unregister or suspend the server by using the **Actions** menu. Suspending a proxy prevents upcoming backup jobs from using the proxy, and jobs that use a suspended or unregistered proxy will run locally, which may impact performance. You can complete maintenance tasks on the proxy while it is suspended. To resume usage of the proxy, select **Actions** > **Resume**.

After successful registration, the service vadp is started on the proxy machine. A log file vadp.log is generated in /opt/IBM/SPP/logs directory.

6. Repeat the previous steps for each proxy you want to create.

The connection between the IBM Spectrum Protect Plus virtual appliance and a registered VADP proxy is a bidirectional connection that requires the IBM Spectrum Protect Plus virtual appliance to have connectivity to the VADP proxy, and the VADP proxy to have connectivity to the IBM Spectrum Protect Plus virtual appliance. To ensure a proper connection from the IBM Spectrum Protect Plus virtual appliance to the VADP proxy, verify that the IBM Spectrum Protect Plus virtual appliance can ping the VADP proxy by completing the following steps:

- 1. Connect to the command line for the IBM Spectrum Protect Plus virtual appliance by using the Secure Shell (SSH) network protocol.
- 2. Execute ping <vadp ip>, where <vadp ip> is the resolvable IP address of the VADP proxy.

If the ping fails, ensure that the IP address of the VADP proxy is resolvable and is addressable by the IBM Spectrum Protect Plus appliance and that a route exists from the IBM Spectrum Protect Plus appliance to the VADP proxy. If the ping succeeds, ensure there is a proper connection from the VADP proxy to the IBM Spectrum Protect Plus virtual appliance by performing the following procedure:

- 1. Connect to the command line for the VADP proxy by using Secure Shell (SSH) network protocol.
- 2. Execute ping <spectrum\_protect\_plus\_ip>, where <spectrum\_protect\_plus\_ip> is the resolvable IP address of the IBM Spectrum Protect Plus virtual appliance.

If the ping fails, ensure that the IP address of the IBM Spectrum Protect Plus virtual appliance is resolvable and is addressable by the VADP proxy. Ensure that a route exists from the VADP proxy to the IBM Spectrum Protect Plus virtual appliance.

### What to do next

After you create the VADP proxies, complete the following action:

Action	How to
Run the VMware backup job.	See <u>"Backing up VMware data" on page 97</u> .
	The proxies are indicated in the job log by a log message similar to the following text:
	Run remote vmdkbackup of MicroService: http:// <proxy></proxy>
	nodename, IP:proxy_IP_address

#### **Related tasks**

"Setting options for VADP proxies" on page 105

You can create VADP proxies to run VMware backup jobs with IBM Spectrum Protect Plus in Linux environments.

### **Setting options for VADP proxies**

You can create VADP proxies to run VMware backup jobs with IBM Spectrum Protect Plus in Linux environments.

#### **Procedure**

To set options for VMware VADP proxies, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **VADP Proxy**.
- 2. Click the ellipses icon \*\*\* to view available options for the proxy.
- 3. Complete the following fields in the Set VADP Proxy Options pane:

#### Site

Assign a site to the proxy.

#### User

Select a previously entered user name for the provider. To enable automatic updates of the VADP proxy, a previously entered user name must be selected.

### **Transport Modes**

Set the transport modes to be used by the proxy. For more information about VMware transport modes, see Virtual Disk Transport Methods.

#### **Enable NBDSSL Compression**

If you selected the NBDSSL transport mode, enable compression to increase the performance of data transfers.

To turn off compression, select **disabled**.

# Log retention in days

Set the number of days to retain logs before they are deleted.

### Read and write buffer size

Set the buffer size of the data transfer, measured in bytes.

#### **Block size of NFS volume**

Set the block size to be used by the mounted NFS volume, measured in bytes.

### Softcap task limit

Set the number of concurrent VMs that a proxy can process. If **Use All Resources** is selected, the number of CPUs on the proxy determines the task limit based on the following formula:

1 CPU = 1 VMDK

A CPU is the smallest hardware unit capable of executing a thread. The number of CPUs on a proxy is determined by using the 1scpu command.

#### What to do next

After setting the VADP proxy options, complete the following actions:

Action	How to
Run the VMware backup job.	See <u>"Backing up VMware data" on page 97</u> .
Uninstall the proxies when you cease running the VMware backup jobs.	See <u>"Uninstalling VADP proxies" on page 106</u> .

#### **Related tasks**

"Creating VADP proxies" on page 103

You can create VADP proxies to run VMware backup jobs with IBM Spectrum Protect Plus in Linux environments.

### **Uninstalling VADP proxies**

You can remove a VADP proxies from your IBM Spectrum Protect Plus environment.

#### **Procedure**

To uninstall VADP proxies from your IBM Spectrum Protect Plus, complete the following steps:

- 1. From a command prompt, navigate to the directory /opt/IBM/SPP/uninstall on the proxy host system.
- 2. Run the following command:
  - ./uninstall\_vmdkbackup

# **Restoring VMware data**

VMware restore jobs support Instant VM Restore and Instant Disk Restore scenarios, which are created automatically based on the selected source.

### Before you begin

Complete the following tasks:

- Ensure that a VMware backup job was run at least once. For instructions, see "Backing up VMware data" on page 97.
- Before an IBM Spectrum Protect Plus user can complete backup and restore operations, roles must be
  assigned to the user. Grant users access to hypervisors and backup and restore operations through the
  Accounts pane. Roles and associated permissions are assigned during user account creation. For more
  information, see Chapter 13, "Managing user access," on page 275 and "Managing user accounts" on
  page 283.
- The size of a virtual machine that is restored from a vSnap offload to an IBM Spectrum Protect restore point will be equal to the thick provisioned size of the virtual machine, regardless of source provisioning due to the use of NFS datastores during the offload. The full size of the data must be transferred even if it is unallocated in the source virtual machine.
- Ensure that the destination that you plan to use for the restore job is registered in IBM Spectrum Protect Plus. This requirement applies to restore jobs that restore data to original hosts or clusters.
- Windows file indexing and file restore on volumes residing on dynamic disks is not supported.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

• When restoring a virtual machine using clone mode and using original IP configuration, ensure that credentials are established through the Guest OS Username and Guest OS Password option within the backup job definition.

### **About this task**

If a VMDK is selected for restore operation, IBM Spectrum Protect Plus automatically presents options for an Instant Disk restore job, which provides instant writable access to data and application restore points. An IBM Spectrum Protect Plus snapshot is mapped to a target server where it can be accessed or copied as required.

All other sources are restored through Instant VM restore jobs, which can be run in the following modes:

#### **Test mode**

Test mode creates temporary virtual machines for development or testing, snapshot verification, and disaster recovery verification on a scheduled, repeatable basis without affecting production environments. Test machines are kept running as long as needed to complete testing and verification and are then cleaned up. Through fenced networking, you can establish a safe environment to test your jobs without interfering with virtual machines used for production. Virtual machines that are created in test mode are also given unique names and identifiers to avoid conflicts within your production environment. For instructions for creating a fenced network, see "Creating a fenced network through a VMware restore job" on page 112.

#### Clone mode

Clone mode creates copies of virtual machines for use cases that require permanent or long-running copies for data mining or duplication of a test environment in a fenced network. Virtual machines created in clone mode are also given unique names and identifiers to avoid conflicts within your production environment. With clone mode, you must be sensitive to resource consumption because clone mode creates permanent or long-term virtual machines.

#### **Production mode**

Production mode enables disaster recovery at the local site from primary storage or a remote disaster recovery site, replacing original machine images with recovery images. All configurations are carried over as part of the recovery, including names and identifiers, and all copy data jobs associated with the virtual machine continue to run.

### **Procedure**

To define a VMware restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Hypervisors** > **VMware** > **Create Restore Job** to open the "Snapshot restore" wizard.

#### Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore Job > VMware.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, take the following actions:
  - a) Review the available sources, including virtual machines (VMs) and virtual disks (VDisks). Use the **View** filter to toggle the displayed sources to show hosts and clusters, VMs, or tags and categories. You can expand a source by clicking its name.
    - You can also enter all or part of a name in the **Search for** box to locate VMs that match the search criteria. You can use the wildcard character (\*) to represent all or part of a name. For example, vm2\* represents all resources that begin with "vm2".
  - b) Click the plus icon ext to the item that you want to add to the restore list next to the list of sources. You can add more than one item of the same type (VM or virtual disk).

To remove an item from the restore list, click the minus icon next to the item.

- c) Click Next.
- 3. On the **Source snapshot** page, specify the instance of the VM or virtual disk that you want to restore. Complete the following fields and click **Next** to continue. Some fields are not displayed until you select a related field.

select a related field	
Option	Description
Restore Type	Select the type of restore job:
	On-demand
	Runs a one-time restore operation.
	Recurring  Creates a repeating point-in-time restore job that runs on a schedule.
B. d. a. l. a. d. a.	
Restore Location Type	Select a type of location from which to restore data:
. , , ,	Site The site where snapshots were backed up. The site is defined on the
	System Configuration > Site pane.
	Cloud Offload
	The cloud server where snapshots were offloaded. The cloud server is defined on the <b>System Configuration</b> > <b>Backup Storage</b> > <b>Cloud</b> pane.
	Repository Offload
	The repository server where snapshots were offloaded. The repository server is defined on the <b>System Configuration</b> > <b>Backup Storage</b> > <b>Repository Server</b> pane.
	Cloud Archive
	The cloud server on which snapshots were archived. The cloud server is defined on the <b>System Configuration</b> > <b>Backup Storage</b> > <b>Cloud</b> pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	Demo
	The demonstration site from which to restore snapshots.
	Primary  The primary site leastion from which to restore enoughets
	The primary site location from which to restore snapshots.
	Secondary  The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand restore operations, specify a range of dates to show the available snapshots within that range.
Restore Point	For on-demand restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.

Option	Description
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

4. On the **Set destination** page, specify the instance you would like to restore for each chosen source and click **Next**:

### Original ESX Host or Cluster

Select this option to restore data to the original host or cluster.

#### **Alternate ESX Host or Cluster**

Select this option to restore data to a local destination that is different from the original host or cluster, and then select the alternate location from the available resources. Test and production networks can be configured on the alternate location to create a fenced network, which keeps virtual machines used for testing from interfering with virtual machines used for production. From the **vCenters** section, select an alternative location. You can filter the alternative locations by either hosts or clusters.

In the **VM Folder Destination** field, enter the virtual machine folder path on the destination datastore. The directory will be created if it does not exist. Use "/" as the root virtual machine folder of the targeted datastore.

#### ESX host if vCenter is down

Select this option to bypass vCenter Server and to restore data directly to an ESXi host. In other restore scenarios, actions are completed through vCenter Server. If vCenter Server is unavailable, this option restores the virtual machine or virtual machines that contain the components that vCenter Server is dependent on.

When you select an ESXi host, you must specify the host user. You can select an existing user for the host or create a new one.

To create a user, enter a user name, the user ID, and the user password.

If the ESXi host is attached to a domain, the user ID follows the default  $domain \setminus name$  format. If the user is a local administrator, use the  $local\_administrator$  format.

To restore to an ESXi host, the host must have a standard switch or a distributed switch with ephemeral binding. Review the information in "Restoring data when vCenter Server or other management VMs are not accessible" on page 113 to ensure that you have the correct environment configured to use this option.

- 5. On the **Set datastore** page, take the following actions:
  - If you are restoring data to an alternate ESX host or cluster, select the destination datastore and click **Next**.
  - If you are restoring data to the original ESX Host or cluster, you do not need to set a datastore. Click **Next**.
- 6. On the **Set network** page, specify the network settings to use for each chosen source and click **Next**.
  - If you are restoring data to the original ESX host or cluster, specify the following network settings:

### Allow system to define IP configuration

Select this option to allow your operating system to define the destination IP address. During a test mode restore operation, the destination virtual machine receives a new MAC address along with an associated NIC. Depending on your operating system, a new IP address can be assigned based on the original NIC of the virtual machine, or assigned through DHCP. During a production mode restore, the MAC address does not change; therefore, the IP address should be retained.

### Use original IP configuration

Select this option to restore to the original host or cluster using your predefined IP address configuration. During the restore operation, the destination virtual machine receives a new MAC address, but the IP address is retained.

- If you are restoring data to an alternate ESX host or cluster, complete the following steps:
  - a. In the **Production** and **Test** fields, set virtual networks for production and test restore job runs. Destination network settings for production and test environments should point to different locations to create a fenced network, which keeps virtual machines used for testing from interfering with virtual machines that are used for production. The networks that are associated with test and production modes will be used when the restore job is run in the associated mode.
  - b. Set an IP address or subnet mask for virtual machines to be repurposed for development, testing, or disaster recovery use cases. Supported mapping types include IP to IP, IP to DHCP, and subnet to subnet. Virtual machines that contain multiple NICs are supported.

Take one of the following actions:

- To allow your operating system to define the destination subnets and IP addresses, click
   Use system defined subnets and IP addresses for VM guest OS on destination.
- To use your predefined subnets and IP addresses, click Use original subnets and IP addresses for VM guest OS on destination.
- To create a new mapping configuration, select Add mappings for subnets and IP addresses for VM guest OS on destination, click Add Mapping, and enter the IP address of the source machine in the Add Source Subnet or IP Address field.

Choose one of the following network protocols:

- Select **DHCP** to automatically select an IP and related configuration information if DHCP is available on the selected source.
- Select **Static** to enter a specific subnet or IP address, subnet mask, gateway, and DNS. The **Subnet / IP Address**, **Subnet Mask**, and **Gateway** are required fields. If a subnet is entered as a source, a subnet must also be entered as a destination.

**Note:** When a mapping is added, the source IP address must be entered into the field by the + button. The destination IP address information should be entered into the **Subnet / IP Address, Subnet Mask,** and **Gateway** fields. Re-addressing can only be performed on machines with VMware Tools installed prior to executing the backup job that is to be restored.

IP reconfiguration is skipped for virtual machines if a static IP is used but no suitable subnet mapping is found, or if the source virtual machine is powered off and there is more than one associated NIC. In a Windows environment, if a virtual machine uses DHCP only, then IP reconfiguration is skipped for that virtual machine. In a Linux environment, all addresses are assumed to be static, and only IP mapping will be available.

- 7. On the **Restore methods**, select the restore method to be used for source selection. Set the VMware restore job to run in test, production, or clone mode by default. After the job is created, it can be run in production or clone mode through the **Job Sessions** pane. You can also change the name of the restored VM by entering the new VM name in the **Rename VM (optional)** field. Click **Next** to continue.
- 8. On the **Job Options (optional)** page, configure advanced options and click **Next**.

### Make IA® clone resource permanent

Enable this option to move the virtual disk to permanent storage and clean up temporary resources. This action is accomplished by starting a vMotion operation for the resources in the background. The destination of the vMotion operation is the VM Configuration Datastore. The Instant Access disk is still available for read/write operations during this operation.

#### Power on after recovery

Toggle the power state of a virtual machine after a recovery is performed. Virtual machines are powered on in the order in which they are recovered, as set in the Source step.

**Restriction:** Restored virtual machine templates cannot be powered on after recovery.

#### Overwrite virtual machine

Enable this option to allow the restore job to overwrite the selected virtual machine. By default, this option is disabled.

### Continue with restore even if it fails

Toggle the recovery of a resource in a series if the previous resource recovery fails. If disabled, the restore job stops if the recovery of a resource fails.

# Run cleanup immediately on job failure

Enable this option to automatically clean up allocated resources as part of a restore job if the virtual machine recovery fails.

### Allow to overwrite and force cleanup of pending old sessions

Enable this option to allow a scheduled session of a recovery job to force an existing pending session to clean up associated resources so the new session can run. Disable this option to keep an existing test environment running without being cleaned up.

# **Restore VM tags**

Enable this option to restore tags that are applied to virtual machines through vSphere.

### Append suffix to virtual machine name

Enter a suffix to add to the names of restored virtual machines.

### Prepend prefix to virtual machine name

Enter a prefix to add to the names of restored virtual machines.

- 9. Optional: On the **Apply scripts** page, choose the following script options and click **Next**.
  - Select Pre-script to select an uploaded script, and an application or script server where the
    prescript runs. To select an application server where the script will run, clear the Use Script
    Server check box. Go to the System Configuration > Script page to configure scripts and script
    servers.
  - Select Post-script to select an uploaded script and an application or script server where the
    postscript runs. To select an application server where the script runs, clear the Use Script Server
    check box. Navigate to the System Configuration > Script page to configure scripts and script
    servers.
  - Select **Continue job/task on script error** to continue running the job when the script that is associated with the job fails. When this option is enabled and the prescript completes with a nonzero return code, the backup or restore job continues to run and the prescript task status returns COMPLETED. If a postscript completes with a nonzero return code, the postscript task status returns COMPLETED. When this option is not selected, the backup or restore job does not run, and the prescript or postscript task status returns with a FAILED status.
- 10. Take one of the following actions on the **Schedule** page:
  - To run an on-demand job, click Next.
  - To set up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 11. On the **Review** page, review your restore job settings and click **Submit** to create the job.

On-demand jobs will begin immediately; recurring jobs will begin at the scheduled start time.

#### What to do next

After the job is completed, select one of the following options from the **Actions** menu on the Jobs Sessions or Active Clones sections on the **Restore** pane:

### Cleanup

Destroys the virtual machine and cleans up all associated resources. Because this is a temporary virtual machine to be used for testing, all data is lost when the virtual machine is destroyed.

#### **Move to Production (vMotion)**

Migrates the virtual machine through vMotion to the datastore and the virtual Network defined as the production network.

### Clone (vMotion)

Migrates the virtual machine through vMotion to the datastore and virtual Network defined as the test network.

#### **Related tasks**

"Adding a vCenter Server instance" on page 93

When a vCenter Server instance is added to IBM Spectrum Protect Plus, an inventory of the instance is captured, enabling you to complete backup and restore jobs, as well as run reports.

### Creating a fenced network through a VMware restore job

Through fenced networking, you can establish a safe environment to test your jobs without interfering with virtual machines that are used for production. Fenced networking can be used with jobs that are running in test mode and production mode.

### Before you begin

Create and run a VMware Restore job. For instructions, see "Restoring VMware data" on page 106.

#### **Procedure**

To create a fenced network, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > VMware.
- 2. In the **Restore** pane, review the available restore points of your VMware sources, including virtual machines, VM templates, datastores, folders, and vApps. Use the search function and filters to fine-tune your selection across specific recovery site types. Expand an entry in the **Restore** pane to view individual restore points by date.
- 3. Select restore points and click the add to restore list icon to add the restore point to the Restore List. Click the remove icon to remove items from the Restore List.
- 4. Click **Options** to set the job definition options.
- 5. Select Alternate ESX Host or Cluster, then select an alternate host or cluster from the vCenter list.
- 6. Expand the **Network Settings** section. From the **Production** and **Test** fields, set virtual networks for production and test Restore job runs. Destination network settings for production and test environments should be different locations to create a fenced network, which keeps virtual machines used for testing from interfering with virtual machines used for production. The networks associated with Test and Production will be utilized when the restore job is run in the associated mode. The IP addresses of the target machine can be configured by using the following options:

# Use system defined subnets and IP addresses for VM guest OS on destination

Select to allow your operating system to define the destination IP address. During a Test Mode restore, the destination virtual machine receives a new MAC address along with an associated NIC. Depending on your operating system, a new IP address can be assigned based on the original NIC of the virtual machine, or assigned through DHCP. During a Production Mode restore operation the MAC address does not change; therefore, the IP address should be retained.

# Use original subnets and IP addresses for VM guest OS on destination

Select to restore to the original host or cluster using your predefined IP address configuration. During a restore, the destination virtual machine receives a new MAC address, but the IP address is retained.

Set the network settings for a restore to an alternate or long distance ESX host or cluster:

From the **Production** and **Test** fields, set virtual networks for production and test restore job runs. Destination network settings for production and test environments should be different locations to create a fenced network, which keeps virtual machines used for testing from interfering with virtual

machines used for production. The networks associated with Test and Production will be utilized when the restore job is run in the associated mode.

Set an IP address or subnet mask for virtual machines to be re-purposed for development/testing or disaster recovery use cases. Supported mapping types include IP to IP, IP to DHCP, and subnet to subnet. Virtual machines containing multiple NICs are supported.

By default, the Use system defined subnets and IP addresses for VM guest OS on destination option is enabled. To use your predefined subnets and IP addresses, select Use original subnets and IP addresses for VM guest OS on destination.

To create a new mapping configuration, select **Add mappings for subnets and IP addresses for VM guest OS on destination**, then click **Add Mapping**. Enter a subnet or IP address in the **Source** field. In the destination field, select **DHCP** to automatically select an IP and related configuration information if DHCP is available on the selected client. Select **Static** to enter a specific subnet or IP address, subnet mask, gateway, and DNS. Note that **Subnet / IP Address**, **Subnet Mask**, and **Gateway** are required fields. If a subnet is entered as a source, a subnet must also be entered as a destination.

IP reconfiguration is skipped for virtual machines if a static IP is used but no suitable subnet mapping is found, or if the source machine is powered off and there is more than one associated NIC. In a Windows environment, if a virtual machine is DHCP only, then IP reconfiguration is skipped for that virtual machine. In a Linux environment all addresses are assumed to be static, and only IP mapping will be available.

#### **Destination Datastore**

Set the destination datastore for a restore to an alternate ESX host or cluster.

### **VM Folder Destination**

Enter the VM folder path on the destination datastore. Note that the directory will be created if it does not exist. Use "/" as the root VM folder of the targeted datastore.

- 7. Click **Save** to save the policy options.
- 8. After the job is complete, select one of the following options from the **Actions** menu on the Jobs Sessions or Active Clones sections on the **Restore** pane:

### Cleanup

Destroys the virtual machine and cleans up all associated resources. Since this is a temporary/testing virtual machine, all data is lost when the virtual machine is destroyed.

### **Move to Production (vMotion)**

Migrates the virtual machine through vMotion to the Datastore and the Virtual Network defined as the "Production" Network.

#### Clone (vMotion)

Migrates the virtual machine through vMotion to the Datastore and Virtual Network defined as the "Test" network.

### **Related tasks**

"Adding a vCenter Server instance" on page 93

When a vCenter Server instance is added to IBM Spectrum Protect Plus, an inventory of the instance is captured, enabling you to complete backup and restore jobs, as well as run reports.

#### Restoring data when vCenter Server or other management VMs are not accessible

IBM Spectrum Protect Plus provides an option to automatically restore data by using an ESXi host if vCenter Server or one of the components that it uses are not accessible. This option restores the virtual machines that contain the components that vCenter Server uses.

#### Before you begin

To complete this procedure, you must be familiar with the ESXi and vCenter Server user interfaces.

#### **About this task**

vCenter Server uses the following components:

- Platform Services Controller (PSC)
- Software-Defined Data Center (SDDC)
- Active Directory (AD)
- Domain Name System (DNS) servers

To use the **ESX host if vCenter is down** option, the ESXi host must have a standard switch or a distributed switch. The distributed switch must have ephemeral binding. If one or both of these switches are available, you can run a restore operation in IBM Spectrum Protect Plus with the option enabled as described in "Restoring VMware data" on page 106 and no further manual configuration is required.

If neither of these switches is available, you must complete the following steps before you can use the **ESX host if vCenter is down** option.

#### **Procedure**

- 1. Connect to the destination ESXi host user interface and create a standard virtual switch. The new switch has no port groups or uplinks.
- 2. Use the Secure Shell (SSH) protocol to connect to the ESXi host.
- 3. List the distributed switches that are configured on the ESXi host by issuing the following command:

```
#esxcli network vswitch dvs vmware list
```

- 4. Identify the physical network interface card (NIC) and the port group of the distributed switch that you want to use for the restore operation.
- 5. Remove the physical NIC and port group from the distributed switch by issuing the following command:

```
#esxcfg-vswitch -Q physical_vnic -V port_group switch_name
```

6. Add the physical NIC and port group to the new standard switch by issuing the following command:

```
\#esxcli network vswitch standard uplink add --uplink-name=physical\_vnic --vswitch-name=new\_standard\_vswitch
```

7. In the ESXi host user interface, add a temporary port group and select the standard switch that you created in step "1" on page 114.

The standard switch has one port group and one uplink.

8. Run a restore operation in IBM Spectrum Protect Plus with the **ESX host if vCenter is down** option enabled.

For instructions about running a restore operation, see "Restoring VMware data" on page 106.

- 9. In the ESXi host user interface for the ESXi host, power on the VMs that are restored.
- 10. Log in to the vCenter Server user interface and start the migration of the management VMs from the temporary port group that you created in step "7" on page 114 to an available distributed port group.
- 11. After all of the VMs are migrated to the original port group, reincorporate the physical NIC and the port group into the original distributed switch by taking the following actions. For example purposes, the following commands reference a virtualized Network Interface Card (VNIC) named vmnic0 that is part of port group 64.
  - a. Remove the network cards (known as vmnics) from a standard switch by issuing the following command:

```
#esxcli network vswitch standard uplink remove --uplink-name=vmnic --vswitch-name=vSwitch
```

For example:

#esxcli network vswitch standard uplink remove --uplink-name=vmnic0 --vswitchname=vered\_recovery

b. Add network cards to the distributed switch by issuing the following command:

#esxcfg-vswitch -P vmnic -V unused\_distributed\_switch\_port\_ID distributed\_switch

For example:

#esxcfg-vswitch -P vmnic0 -V 64 SDDC-Dswitch-Private

- 12. Delete the temporary port group and the standard switch from the ESXi host user interface.
- 13. After the VMs are migrated and accessible, use the ESXi host user interface to unregister, but not delete, the old VMs if the original host is reachable.

By using this method, you avoid creating duplicated information such as names, Media Access Control (MAC) addresses, operating system level IDs, and VM Universal Unique Identifiers (UUIDs). You must complete this step even if you are using a new datastore.

In some vSphere or ESXi versions, the unregister operation can be completed by using the **Remove from inventory** option. This option unregisters a VM from the vCenter Server catalog, but leaves VMDK files on the datastore where the files consume storage space. After you have fully recovered the VM and the environment is successfully running, you can regain the space by manually removing these files from the datastore.

# **Backing up and restoring Hyper-V data**

To protect Hyper-V data, first add Hyper-V servers in IBM Spectrum Protect Plus, and then create jobs for backup and restore operations for the content of the servers.

Ensure that your Hyper-V environment meets the system requirements in "Hypervisor requirements" on page 21.

# Adding a Hyper-V server

When a Hyper-V server is added to IBM Spectrum Protect Plus, an inventory of the server is captured, enabling you to complete backup and restore jobs, as well as run reports.

### Before you begin

Note the following considerations and procedures before adding a Hyper-V server to IBM Spectrum Protect Plus:

- Hyper-V servers can be registered using a DNS name or IP address. DNS names must be resolvable by IBM Spectrum Protect Plus. If the Hyper-V server is part of a cluster, all nodes in the cluster must be resolvable through DNS. If DNS is not available, the server must be added to the /etc/hosts file on the IBM Spectrum Protect Plus appliance. If more than one Hyper-V server is set up in a cluster environment, all of the servers must be added to/etc/hosts. When registering the cluster in IBM Spectrum Protect Plus, register the Failover Cluster Manager.
- All Hyper-V servers, including cluster nodes, must have the Microsoft iSCSI initiator Service running in their Services list. Set the service to Automatic so that it is available when the machine boots.
- Add the user to the local administrator group on the Hyper-V server.

#### **Procedure**

To add a Hyper-V server, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > Hyper-V.
- 2. Click Manage Hyper-V Server.
- 3. Click Add Hyper-V Server.
- 4. Populate the fields in the **Server Properties** pane:

#### Hostname/IP

Enter the resolvable IP address or a resolvable path and machine name.

### Use existing user

Enable to select a previously entered user name and password for the server.

#### Username

Enter your user name for the server.

#### **Password**

Enter your password for the server.

#### Port

Enter the communications port of the server you are adding. The typical default port is 5985.

Select the Use SSL check box to enable an encrypted Secure Sockets Layer (SSL) connection.

If you do not select **Use SSL**, you must complete additional steps on the Hyper-V server. See "Enabling WinRM for connection to Hyper-V servers" on page 116.

5. In the **Options** section, configure the following option:

### Maximum number of VMs to process concurrently per Hyper-V server

Set the maximum number of concurrent virtual machine snapshots to process on the Hyper-V server.

6. Click **Save**. IBM Spectrum Protect Plus confirms a network connection, adds the server to the database, and then catalogs the server.

If a message appears indicating that the connection is unsuccessful, review your entries. If your entries are correct and the connection is unsuccessful, contact a system administrator to review the connections.

### What to do next

After you add the Hyper-V server, complete the following action:

Action	How to
Assign user permissions to the hypervisor.	See <u>"Creating a role" on page 280</u> .

#### **Related tasks**

"Backing up Hyper-V data" on page 117

Use a backup job to back up Hyper-V data with snapshots.

### "Restoring Hyper-V data" on page 121

Hyper-V restore jobs support Instant VM Restore and Instant Disk Restore scenarios, which are created automatically based on the selected source.

# **Enabling WinRM for connection to Hyper-V servers**

If you cannot use SSL to enable encrypted network traffic between IBM Spectrum Protect Plus Hyper-V servers, you must configure WinRM on the host to allow unencrypted network traffic. Ensure that you understand the security risks that are associated with allowing unencrypted network traffic.

#### **Procedure**

To configure WinRM for connection to Hyper-V hosts:

- 1. On the Hyper-V host system, log in with an administrator account.
- 2. Open a Windows command prompt. If User Account Control (UAC) is enabled, you must open the command prompt with elevated privileges by running with the "Run as administrator" option enabled.
- 3. Enter the following command to configure WinRM to allow unencrypted network traffic:

```
winrm s winrm/config/service @{AllowUnencrypted="true"}
```

4. Verify that the AllowUnencrypted option is set to true through the following command:

### **Detecting Hyper-V resources**

Hyper-V resources are automatically detected after the Hyper-V server is added to IBM Spectrum Protect Plus. However, you can run an inventory job to detect any changes that occurred since the server was added.

#### **Procedure**

To run an inventory job, complete the following steps:

- 1. In the navigation pane, click **Manage Protection** > **Hypervisors** > **Hyper-V**.
- 2. In the list of Hyper-V servers, select a server or click the link for the server to navigate to the resource that you want. For example, if you want to run an inventory job for an individual virtual machine in a server, click the server link and then select a virtual machine.
- 3. Click Run Inventory.

# Testing the connection to a Hyper-V Server virtual machine

You can test the connection to Hyper-V Server virtual machine. The test function verifies communication with the virtual machine and tests DNS settings between the IBM Spectrum Protect virtual appliance and the virtual machine.

### **Procedure**

ı

To test the connection, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > Hyper-V.
- 2. In the list of Hyper-V Servers, click the link for a Hyper-V Server virtual machine to navigate to the individual virtual machines.
- 3. Select a virtual machine, and then click **Select Options**.
- 4. Select **Use existing user**.
- 5. Select a user in the **Select user** list.
- 6. Click Test.

### Backing up Hyper-V data

Use a backup job to back up Hyper-V data with snapshots.

### Before you begin

Note the following procedures and considerations before creating a backup job definition:

- Register the providers that you want to back up. For more information see <u>"Adding a Hyper-V server" on</u> page 115
- Configure SLA policies. For instructions, see "Create backup policies" on page 70.
- Hyper-V Backup and Restore jobs require the installation of the latest Hyper-V integration services.

For Microsoft Windows environments, see <u>Supported Windows guest operating systems for Hyper-V on</u> Windows Server.

For Linux environments, see Supported Linux and FreeBSD virtual machines for Hyper-V on Windows.

- All Hyper-V servers, including cluster nodes, must have the Microsoft iSCSI initiator Service running in their Services list. Set the service to Automatic so that it is available when the machine boots.
- Before an IBM Spectrum Protect Plus user can complete backup and restore operations, roles must be assigned to the user. Grant users access to hypervisors and backup and restore operations through the **Accounts** pane. Roles and associated permissions are assigned during user account creation. For more information, see <u>Chapter 13</u>, "Managing user access," on page 275 and "Managing user accounts" on page 283.

- If a virtual machine is associated with multiple SLA Policies, ensure that the policies are not scheduled to run concurrently. Either schedule the SLA Policies to run with a significant amount of time between them, or combine them into a single SLA policy.
- If the IP address of the IBM Spectrum Protect Plus appliance is changed after an initial Hyper-V base backup is created, the target IQN of the Hyper-V resource may be left in a bad state. To correct this issue, from the Microsoft iSCSI Initiator tool, click the **Discovery** tab. Select the old IP address, then click **Remove**. Click the **Target** tab and disconnect the reconnecting session.
- If a VM is protected by an SLA policy, the backups of the VM will be retained based on the retention parameters of the SLA policy, even if the VM is removed.

#### **About this task**

**Restriction:** File cataloging, backup, point-in-time restores, and other operations that invoke the Windows agent will fail if a non-default local administrator is entered as the **Guest OS Username** when defining a backup job. A non-default local administrator is any user that has been created in the guest OS and has been granted the administrator role.

This occurs if the registry key LocalAccountTokenFilterPolicy in [HKLM\SOFTWARE\Microsoft \Windows\CurrentVersion\Policies\System] is set to 0 or not set. If the parameter is set to 0 or not set, a local non-default administrator cannot interact with WinRM, which is the protocol IBM Spectrum Protect Plus uses to install the Windows agent for file cataloging, send commands to this agent, and get results from it.

Set the LocalAccountTokenFilterPolicy registry key to 1 on the Windows guest that is being backed up with Catalog File Metadata enabled. If the key does not exist, navigate to [HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Policies\System] and add a DWord Registry key named LocalAccountTokenFilterPolicy with a value of 1.

#### **Procedure**

ı

To define a Hyper-V backup job, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Hypervisors > Hyper-V.
- 2. Select resources to back up.
  - Use the search function to search for available resources and toggle the displayed resources through the **View** filter. Available options are **VMs** and **Datastore**.
- 3. Click **Select SLA Policy** to add one or more SLA policies that meet your backup data criteria to the job definition.
- 4. To create the job definition by using default options, click **Save**.

The job runs as defined by the SLA policies that you selected. To run the job manually, click **Jobs and Operations** > **Schedule**. Select the job and click **Actions** > **Start**.

**Tip**: The **Run**button is only enabled for a single hypervisor backup, and the hypervisor must have an SLA policy applied.

5. To edit options before you start the job, click the edit icon in the table **Select Options**.

In the **Backup Options** section, set the following job definition options:

#### Skip Read-only datastores

Enable to skip datastores mounted as read-only.

### **Skip temporary datastores mounted for Instant Access**

Enable to exclude temporary Instant Access datastores from the backup job definition.

### **Priority**

Set the backup priority of the selected resource. Resources with a higher priority setting are backed up first in the job. Click the resource that you want to prioritize in the **VMware Backup** section, and then set the backup priority in the **Priority** field. Set 1 for the highest priority resource or 10 for the lowest. When a priority value is not set, automatically assigns a priority of 5 is set by default.

In the **Snapshot Options** section, set the following job definition options:

### Make VM snapshot application/file system consistent

Enable this option to turn on application or filesystem consistency for the virtual machine snapshot.

### VM Snapshot retry attempts

Set the number of times IBM Spectrum Protect Plus should attempt to snapshot a virtual machine before canceling the job.

In the **Agent Options** section, set the following job definition options:

### **Truncate SQL logs**

To truncate application logs for SQL during the Backup job, enable the **Truncate SQL logs** option. Note that credentials must be established for the associated virtual machine through the Guest OS Username and Guest OS Password option within the backup job definition. The user identity follows the default <code>domain\name</code> format if the virtual machine is attached to a domain. The format <code>local\_administrator</code> is used if the user is a local administrator.

The user identity must have local administrator privileges. Additionally, on the SQL server, the system login credential must have SQL sysadmin permissions enabled, as well as the **Log on as a service** right. For more information about this right, see Add the Log on as a service Right to an Account.

IBM Spectrum Protect Plus generates logs pertaining to the log truncation function and copies them to the following location on the IBM Spectrum Protect Plus appliance:

/data/log/guestdeployer/latest\_date/latest\_entry/vm\_name

Where *latest\_date* is the date that the backup job and log truncation occurred, *latest\_entry* is the universally unique identifier (UUID) for the job, and *vm\_name* is the hostname or IP address of the VM where the log truncation occurred.

**Restriction:** File indexing and file restore are not supported from restore points that were offloaded to an IBM Spectrum Protect server.

### Catalog file metadata

To turn on file indexing for the associated snapshot, enable the Catalog file metadata option. After file indexing is complete, individual files can be restored by using the **File Restore** pane in IBM Spectrum Protect Plus. Note that credentials must be established for the associated virtual machine by using an SSH key, or a Guest OS Username and Guest OS Password option in the backup job definition. Ensure that the virtual machine can be accessed from the IBM Spectrum Protect Plus appliance either by using DNS or hostname. Note that SSH keys are not a valid authorization mechanism for Windows platforms.

### **Exclude Files**

Enter directories to skip when file indexing is performed. Files within these directories are not added to the IBM Spectrum Protect Plus catalog and are not available for file recovery. Directories can be excluded through an exact match or with wildcard asterisks specified before the pattern (\*test) or after the pattern (test\*). Multiple asterisk wildcards are also supported in a single pattern. Patterns support standard alphanumeric characters as well as the following special characters: - \_ and \*. Separate multiple filters with a semicolon.

### Use existing user

Enable to select a previously entered username and password for the provider.

# **Guest OS Username/Password**

For some tasks (such as cataloging file metadata, file restore, and IP reconfiguration), credentials must be established for the associated virtual machine. Enter the username and password, and ensure that the virtual machine can be accessed from the IBM Spectrum Protect Plus appliance either through DNS or hostname.

The default security policy uses the Windows NTLM protocol, and the user identity follows the default domain\name format if the Hyper-V virtual machine is attached to a domain. The format local\_administrator is used if the user is a local administrator.

6. To troubleshoot a connection to a hypervisor virtual machine, use the **Test** function.

The **Test** function verifies communication with the virtual machine and tests DNS settings between the IBM Spectrum Protect Plus appliance and the virtual machine. To test a connection, select a single virtual machine, then click **Select Options**. Select **Use existing user** and select a previously entered user name and password for the resource. The **Test** button displays to the right of the **Save** button in the **Options** section. Click **Test**.

- 7. Click Save.
- 8. To configure additional options, click the **Policy Options** field that is associated with the job in the **SLA Policy Status** section. Set the additional policy options:

# **Pre-scripts and Post-scripts**

Run a pre-script or a post-script. Pre-scripts and post-scripts are scripts that can be run before or after a job runs at the job level. Windows-based machines support Batch and PowerShell scripts while Linux-based machines support shell scripts.

In the **Pre-script** or **Post-script** section, select an uploaded script and a script server where the script will run. Scripts and script servers are configured on the **System Configuration** > **Script** page.

To continue running the job if the script associated with the job fails, select **Continue job/task on script error**.

When this option is enabled, if a pre-script or post-script completes processing with a non-zero return code, the backup or restore operation is attempted and the pre-script task status is reported as COMPLETED. If a post-script completes with a non-zero return code, the post-script task status is reported as COMPLETED.

When this option is disabled, the backup or restore is not attempted, and the pre-script or post-script task status is reported as FAILED.

#### Run inventory before backup

Run an inventory job and capture the latest data of the selected resources before starting the backup job.

#### **Exclude Resources**

Exclude specific resources from the backup job through single or multiple exclusion patterns. Resources can be excluded through an exact match or with wildcard asterisks specified before the pattern (\*test) or after the pattern (test\*).

Multiple asterisk wildcards are also supported in a single pattern. Patterns support standard alphanumeric characters as well as the following special characters: - \_ and \*.

Separate multiple filters with a semicolon.

#### Force Full Backup of Resources

Force base backup operations for specific virtual machines or databases in the backup job definition. Separate multiple resources with a semicolon.

9. To save any additional options that you configured, click **Save**.

#### What to do next

After you define a backup job, complete the following action:

Action	How to
Create a Hyper-V restore job definition.	See <u>"Restoring Hyper-V data" on page 121</u> .

### **Related concepts**

"Configuring scripts for backup and restore operations" on page 234

Prescripts and postscripts are scripts that can be run before or after backup and restore jobs run at the job level. Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts are created locally, uploaded to your environment through the **Script** page, and then applied to job definitions.

#### **Related tasks**

"Starting jobs" on page 232

You can run any job on demand, even if the job is set to run on a schedule.

# **Restoring Hyper-V data**

Hyper-V restore jobs support Instant VM Restore and Instant Disk Restore scenarios, which are created automatically based on the selected source.

### Before you begin

Complete the following tasks:

- Ensure that a Hyper-V backup job was run at least once. For instructions, see <u>"Backing up Hyper-V</u> data" on page 117.
- Ensure that the destination that you plan to use for the restore job is registered in IBM Spectrum Protect Plus. This requirement applies to restore jobs that restore data to original hosts or clusters.
- Ensure that the latest Hyper-V integration services are installed.

For Microsoft Windows environments, see <u>Supported Windows guest operating systems for Hyper-V on</u> Windows Server.

For Linux environments, see Supported Linux and FreeBSD virtual machines for Hyper-V on Windows.

- Ensure that the appropriate roles for restore operations are assigned to the affected users. Grant users access to hypervisors and backup and restore operations in the **Accounts** pane. Roles and associated permissions are assigned during user account creation. For instructions, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275 and "Managing user accounts" on page 283.
- Windows file indexing and file restore on volumes residing on dynamic disks is not supported.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.
- When restoring a virtual machine using clone mode and using original IP configuration, ensure that credentials are established through the Guest OS Username and Guest OS Password option within the backup job definition.

#### About this task

If a Virtual Hard Disk (VHDX) is selected for a restore job, IBM Spectrum Protect Plus automatically presents options for an Instant Disk Restore job, which provides instant writable access to data and application restore points.

An IBM Spectrum Protect Plus snapshot is mapped to a target server where the snapshot can be accessed or copied as required. All other sources are restored by using Instant VM restore jobs, which can be run in the following modes:

### **Test mode**

Test mode creates temporary virtual machines for development, testing, snapshot verification, and disaster recovery verification on a scheduled, repeatable basis without affecting production environments. Test machines are kept running while they are needed to complete testing and verification and are then cleaned up. Through fenced networking, you can establish a safe environment to test your jobs without interfering with virtual machines that are used for production. Virtual machines that are created in test mode are also given unique names and identifiers to avoid conflicts within your production environment.

#### Clone mode

Clone mode creates copies of virtual machines for use cases that require permanent or long-running copies for data mining or duplication of a test environment in a fenced network. Virtual machines that are created in clone mode are also given unique names and identifiers to avoid conflicts within your production environment. With clone mode, you must be sensitive to resource consumption because clone mode creates permanent or long-term virtual machines.

#### **Production mode**

Production mode enables disaster recovery at the local site from primary storage or a remote disaster recovery site, replacing original machine images with recovery images. All configurations are carried over as part of the recovery, including names and identifiers, and all copy data jobs that are associated with the virtual machine continue to run.

**Restriction:** Moving from test mode to production mode is not supported for Hyper-V.

#### **Procedure**

To define a Hyper-V restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Hypervisors** > **Hyper-V** > **Create Restore Job** to open the "Snapshot restore" wizard.

### Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore Job > Hyper-V.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, take the following actions:
  - a) Review the available sources, including virtual machines (VMs) and virtual disks (VDisks). You can expand a source by clicking its name.

You can also enter all or part of a name in the **Search for** box to locate VMs that match the search criteria. You can use the wildcard character (\*) to represent all or part of a name. For example, vm2\* represents all resources that begin with "vm2".

b) Click the plus icon to the item that you want to add to the restore list next to the list of sources. You can add more than one item of the same type (VM or virtual disk).

To remove an item from the restore list, click the minus icon an ext to the item.

- c) Click Next.
- 3. On the **Source snapshot** page, specify the instance of the VM or virtual disk that you want to restore. Complete the following fields and click **Next** to continue. Some fields are not displayed until you select a related field.

Option	Description
Restore Type	Select the type of restore job:
	On-demand Runs a one-time restore operation.  Recurring Creates a repeating point-in-time restore job that runs on a schedule.
Restore Location Type	Select a type of location from which to restore data:  Site  The site where snapshots were backed up. The site is defined on the System  Configuration > Site pane.

Option	Description
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:  Demo  The demonstration site from which to restore snapshots.
	Primary The primary site location from which to restore snapshots.  Secondary The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand restore operations, specify a range of dates to show the available snapshots within that range.
Restore Point	For on-demand restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
for the restore job	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

4. On the **Set destination** page, choose the instance to be restored for the selected source and click **Next**:

### Original Hyper-V Host or Cluster

Select this option to restore data to the original host or cluster.

# Alternate Hyper-V Host or Cluster

Select this option to restore data to a local destination that is different from the original host or cluster, then select the alternative location from the available resources.

In the **VM Folder Destination** field, enter the virtual machine folder path on the destination datastore. Note that the directory will be created if it does not exist. Use "/" as the root virtual machine folder of the targeted datastore.

5. On the **Set datastore** page, take the following actions:

- If you are restoring data to an alternate Hyper-V host or cluster, select the destination datastore and click **Next**.
- If you are restoring data to the original ESX Host or cluster, you do not need to set a datastore. Just click **Next**.
- 6. On the **Set network** page, specify the network settings to use for each chosen source and click **Next**.
  - If you are restoring data to the original Hyper-V host or cluster, specify the following network settings:

#### Allow system to define IP configuration

Select this option to allow your operating system to define the destination IP address. During a test mode restore operation, the destination virtual machine receives a new MAC address along with an associated NIC. Depending on your operating system, a new IP address can be assigned based on the original NIC of the virtual machine, or assigned through DHCP. During a production mode restore the MAC address does not change; therefore the IP address should be retained.

### Use original IP configuration

Select this option to restore to the original host or cluster using your predefined IP address configuration. During the restore operation, the destination virtual machine receives a new MAC address, but the IP address is retained.

- If you are restoring data to an alternate Hyper-V host or cluster, complete the following steps:
  - a. In the **Production** and **Test** fields, set virtual networks for production and test restore job runs. Destination network settings for production and test environments should point to different locations to create a fenced network, which keeps virtual machines used for testing from interfering with virtual machines that are used for production. The networks that are associated with test and production modes will be used when the restore job is run in the associated mode.
  - b. Set an IP address or subnet mask for virtual machines to be repurposed for development, testing, or disaster recovery use cases. Supported mapping types include IP to IP, IP to DHCP, and subnet to subnet. Virtual machines that contain multiple NICs are supported.

Take one of the following actions:

- To allow your operating system to define the destination subnets and IP addresses, click
   Use system defined subnets and IP addresses for VM guest OS on destination.
- To use your predefined subnets and IP addresses, click Use original subnets and IP addresses for VM guest OS on destination.
- To create a new mapping configuration, select Add mappings for subnets and IP addresses for VM guest OS on destination, click Add Mapping, and enter the IP address of the source machine in the Add Source Subnet or IP Address field.

Choose one of the following network protocols:

- Select **DHCP** to automatically select an IP and related configuration information if DHCP is available on the selected source.
- Select **Static** to enter a specific subnet or IP address, subnet mask, gateway, and DNS. The **Subnet / IP Address**, **Subnet Mask**, and **Gateway** are required fields. If a subnet is entered as a source, a subnet must also be entered as a destination.

**Note:** When a mapping is added, the source IP address must be entered into the field by the + button. The destination IP address information should be entered into the **Subnet / IP Address, Subnet Mask,** and **Gateway** fields. Re-addressing can only be performed on machines with VMware Tools installed prior to executing the backup job that is to be restored.

IP reconfiguration is skipped for virtual machines if a static IP is used but no suitable subnet mapping is found, or if the source virtual machine is powered off and there is more than one associated NIC. In a Windows environment, if a virtual machine uses DHCP only, then IP

reconfiguration is skipped for that virtual machine. In a Linux environment, all addresses are assumed to be static, and only IP mapping will be available.

- 7. On the **Restore methods**, select the restore method to be used for source selections. Set the Hyper-V restore job to run in test, production, or clone mode by default. After the job is created, you can run the job in production or clone mode by using the **Job Sessions** pane. You can also change the name of the restored VM by entering the new VM name in the **Rename VM (optional)** field. Click **Next** to continue.
- 8. Optional: On the **Job Options (optional)** page, configure advanced options and click **Next**.

### Make IA clone resource permanent

Enable this option to move the virtual disk to permanent storage and clean up temporary resources. This action is accomplished by starting a vMotion operation for the resources in the background. The destination of the vMotion operation is the VM Configuration Datastore. The Instant Access disk is still available for read/write operations during this operation.

### Power on after recovery

Toggle the power state of a virtual machine after a recovery is run. Virtual machines are powered on in the order in which they are recovered, as set in the Source step.

**Restriction:** Restored virtual machine templates cannot be powered on after recovery.

### Overwrite virtual machine

Enable this option to allow the restore job to overwrite the selected virtual machine. By default, this option is disabled.

#### Continue with restore even if it fails

Toggle the recovery of a resource in a series if the previous resource recovery fails. If disabled, the restore job stops if the recovery of a resource fails.

### Run cleanup immediately on job failure

Enable this option to automatically clean up allocated resources as part of a restore job if the virtual machine recovery fails.

### Allow to overwrite and force cleanup of pending old sessions

Enable this option to allow a scheduled session of a recovery job to force an existing pending session to clean up associated resources so the new session can run. Disable this option to keep an existing test environment running without being cleaned up.

### Append suffix to virtual machine name

Enter a suffix to add to the names of restored virtual machines.

# Prepend prefix to virtual machine name

Enter a prefix to add to the names of restored virtual machines. Click Save to save the policy options.

- 9. Optional: On the Apply scripts page, choose the following script options and click Next.
  - Select Pre-script to select an uploaded script, and an application or script server where the
    prescript runs. To select an application server where the script will run, clear the Use Script
    Server check box. Go to the System Configuration > Script page to configure scripts and script
    servers.
  - Select Post-script to select an uploaded script and an application or script server where the
    postscript runs. To select an application server where the script runs, clear the Use Script Server
    check box. Navigate to the System Configuration > Script page to configure scripts and script
    servers.
  - Select **Continue job/task on script error** to continue running the job when the script that is associated with the job fails. When this option is enabled and the prescript completes with a nonzero return code, the backup or restore job continues to run and the prescript task status returns COMPLETED. If a postscript completes with a nonzero return code, the postscript task status returns COMPLETED. When this option is not selected, the backup or restore job does not run, and the prescript or postscript task status returns with a FAILED status.
- 10. Take one of the following actions on the **Schedule** page:

- To run an on-demand job, click **Next**.
- To set up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 11. On the **Review** page, review your restore job settings and click **Submit** to create the job.

On-demand jobs will begin immediately; recurring jobs will begin at the scheduled start time.

#### What to do next

After the job is complete, select one of the following options from the **Actions** menu on the **Jobs Sessions** or **Active Clones** sections on the **Restore** pane:

### Cleanup

Destroys the virtual machine and cleans up all associated resources. Because this is a temporary virtual machine to be used for testing, all data is lost when the virtual machine is destroyed.

### Clone (migrate)

Migrates the virtual machine to the datastore and virtual network that are defined as the test network.

#### **Related tasks**

"Backing up Hyper-V data" on page 117

Use a backup job to back up Hyper-V data with snapshots.

"Adding a Hyper-V server" on page 115

When a Hyper-V server is added to IBM Spectrum Protect Plus, an inventory of the server is captured, enabling you to complete backup and restore jobs, as well as run reports.

# **Restoring files**

Recover files from snapshots that are created by IBM Spectrum Protect Plus backup jobs. Files can be restored to their original or an alternate location.

### Before you begin

Note the following procedures and considerations before restoring a file:

- Review the file indexing and restore requirements in <u>"File indexing and restore requirements" on page</u> 22.
- Run a backup job with catalog file metadata enabled. Follow these guidelines:
  - Ensure that credentials are established for the associated virtual machine as well as the alternate virtual machine destination through the Guest OS Username and Guest OS Password option within the backup job definition.
  - Ensure that the virtual machine can be accessed from the IBM Spectrum Protect Plus appliance
    either through DNS or hostname. In a Windows environment, the default security policy uses the
    Windows NTLM protocol, and the user identity follows the default domain\name format if the HyperV virtual machine is attached to a domain. The format local\_administrator is used if the user is a
    local administrator.
  - For a file restore to complete successfully, ensure that the user ID that is on the target machine has the necessary ownership permissions for the file that is being restored. If a file was created by a user that differs from the user ID that is restoring the file based on Windows security credentials, the file restore job fails.

### About this task

#### **Restrictions:**

- Encrypted Windows file systems are not supported for file cataloging or file restore.
- File indexing and file restore are not supported from restore points that were offloaded to cloud resources or repository servers.

- When restoring files in a Resilient File System (ReFS) environment, restores from newer versions of Windows Server to earlier versions are not supported. For example, restoring a file from Windows Server 2016 to Windows Server 2012.
- File cataloging, backup, point-in-time restores, and other operations that invoke the Windows agent will fail if a non-default local administrator is entered as the **Guest OS Username** when defining a backup job. A non-default local administrator is any user that has been created in the guest OS and has been granted the administrator role.

This occurs if the registry key LocalAccountTokenFilterPolicy in [HKLM\SOFTWARE\Microsoft \Windows\CurrentVersion\Policies\System] is set to 0 or not set. If the parameter is set to 0 or not set, a local non-default administrator cannot interact with WinRM, which is the protocol IBM Spectrum Protect Plus uses to install the Windows agent for file cataloging, send commands to this agent, and get results from it.

Set the LocalAccountTokenFilterPolicy registry key to 1 on the Windows guest that is being backed up with Catalog File Metadata enabled. If the key does not exist, navigate to [HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Policies\System] and add a DWord Registry key named LocalAccountTokenFilterPolicy with a value of 1.

To help avoid issues that can result from time zone differences, use an NTP server to synchronize time zones across resources. For example, you can synchronize time zones for storage arrays, hypervisors, and application servers that are in your environment.

If the time zones are out of sync, you might experience errors during application registration, metadata cataloging, inventory, backup, or restore, or file restore jobs. For more information about identifying and resolving timer drift, see Time in virtual machine drifts due to hardware timer drift

# **Hyper-V considerations**

Only volumes on SCSI disks are eligible for file cataloging and file restore.

#### **Linux considerations**

If data is located on LVM volumes, the *lvm2-lvmetad* service must be disabled because it can interfere with the ability of IBM Spectrum Protect Plus to mount and resign volume group snapshots or clones. To disable the service, complete the following steps:

1. Run the following commands:

```
systemctl stop lvm2-lvmetad
systemctl disable lvm2-lvmetad
```

2. Edit the/etc/lvm/lvm.conf and specify the following setting:

```
use_lvmetad = 0
```

If data resides on XFS file systems and the version of the xfsprogs package is between 3.2.0 and 4.1.9, the file restore can fail due to a known issue in xfsprogs that causes corruption of a clone or snapshot file system when its UUID is modified. To resolve this issue, update xfsprogs to version 4.2.0 or above. For more information, see Debian Bug report logs.

### **Procedure**

To restore a file, complete the following steps.

- 1. In the navigation pane, click Manage Protection > File Restore.
- 2. Enter a search string to search for a file by name, and then click the search icon . For more information about using the search function, see Appendix A, "Search guidelines," on page 293.
- 3. Optional: You can use filters to fine-tune your search across specific virtual machines, date range in which the file was protected, and virtual machine operating system types.

Searches can also be limited to a specific folder through the **Folder path** field. The **Folder path** field supports wildcards. Position wildcards at the beginning, middle, or end of a string. For example, enter \*Downloads to search within the Downloads folder without entering the preceding path.

**Note:** Only file objects for which a snapshot was taken during the date range that is specified will be visible. For those objects, when the arrow is clicked beside the file object, all previous snapshots for that file object are displayed.

- 4. To restore the file by using default options, click **Restore**. The file is restored to its original location.
- 5. To edit options before restoring the file, click **Options**. Set the file restore options.

### Overwrite existing files/folder

Replace the existing file or folder with the restored file or folder.

### **Destination**

Select to replace the existing file or folder with the restored file or folder.

To restore the file to its original location, select **Restore files to original location**.

To restore to a local destination different from the original location, select **Restore files to alternative location**. Then select the alternate location from available resources by using the navigation menu or the search function.

**Restriction:** A file can be restored to an alternate location only if credentials were established for the alternate virtual machine through the **Guest OS Username/Password** option in the backup job definition.

Enter the virtual machine folder path on the alternate destination in the **Destination Folder** field. If the directory does not exist, it will be created.

Click Save to save the options.

6. To restore the file by using defined options, click **Restore**.

### **Related tasks**

"Backing up VMware data" on page 97

Use a backup job to back up VMware resources such as virtual machines, datastores, folders, vApps, and datacenters with snapshots.

"Restoring VMware data" on page 106

VMware restore jobs support Instant VM Restore and Instant Disk Restore scenarios, which are created automatically based on the selected source.

# **Chapter 8. Protecting applications**

You must register the database applications that you want to protect in IBM Spectrum Protect Plus and then create jobs to back up and restore the databases and resources that are associated with the applications.

**Note:** IBM Spectrum Protect Plus might create folders on application servers when applications are registered with IBM Spectrum Protect Plus. Folders created by IBM Spectrum Protect Plus must remain for the product to function properly. However, if you must remove a folder that was created by IBM Spectrum Protect Plus, unregister the application and IBM Spectrum Protect Plus will clean up the folders that are associated with the registration.

Do not assign more than one application per machine as an application server to a resource group. For example, if Microsoft SQL Server and Microsoft Exchange Server occupy the same machine and both are registered with IBM Spectrum Protect Plus, only one of the applications can be added as an application server to a given resource group.

# Db<sub>2</sub>

After you successfully add your IBM Db2 instances to IBM Spectrum Protect Plus, you can start to protect your Db2 data. Create service level agreements (SLA) policies to back up and maintain Db2 data.

Ensure that your Db2 environment meets the system requirements. For more information, see <u>"Db2"</u> requirements" on page 29.

**Tip:** If your Db2 data is stored in a multi-partitioned environment with multiple hosts, you can protect your Db2 data across each host. Each host in the multi-partitioned environment must be added to IBM Spectrum Protect Plus so that all instances and databases are detected for protection. For more information, see "Adding a Db2 application server" on page 132.

# **Prerequisites for Db2**

All prerequisites for the IBM Spectrum Protect Plus Db2 application server must be met before you start protecting Db2 resources with IBM Spectrum Protect Plus.

Requirements for the IBM Spectrum Protect Plus Db2 application server are available here,  $\underline{\text{Db2}}$  requirements.

### **Space prerequisites**

Ensure that you have enough space on the Db2 database management system, in the volume groups for the backup operation, and on the target volumes for copying files during the restore operation. For more information about space requirements, see <u>Space requirements for Db2 protection</u>. When you are restoring data to an alternative location, allocate extra dedicated volumes for the copy and restore processes. The data paths for table spaces and logs on the target host are the same as the paths on the original host. This setup is needed to allow copying of data from the mounted vSnap to the target host. Ensure that dedicated local database directories are allowed for each database in your volume setup.

### **Multi-partitioned Db2 environments**

In order to protect Db2 multi-partitioned databases, the ACS backup mode must be set to parallel mode. To run parallel backup processing of partitions in your Db2 environment, ensure that one of the following prerequisites is met:

- The Db2 registry variable DB2\_PARALLEL\_ACS is set to YES, for example: db2set DB2\_PARALLEL\_ACS=YES.
- The Db2 registry variable **DB2\_WORKLOAD** is set to SAP.

**Restriction:** The **DB2\_PARALLEL\_ACS** registry variable is available only in certain fix pack levels of Db2. If **DB2\_PARALLEL\_ACS** is not available in your version, you can choose to change **DB2\_WORKLOAD** to SAP.

### More configuration requirements

Ensure that your Db2 environment is configured to meet the following criteria:

- Db2 archive logging is activated, and Db2 is in recoverable mode.
- Ensure that the effective file size **ulimit** -f for the IBM Spectrum Protect Plus agent user and the Db2 instance user, is set to unlimited. Alternatively, set the value to a sufficiently high value to allow copying of the largest database files in your backup and restore jobs. If you change the **ulimit** setting, restart the Db2 instance to finalize the configuration.
- If you are running IBM Spectrum Protect Plus in an AIX or Linux environment, ensure that the installed sudo version is at the recommended level. For more information, see technote 2013790. Then, set sudo privileges as described in "Setting sudo privileges for Db2" on page 132.
- In a Linux environment, ensure that the Linux utility package util-linux-ng or util-linux package is current.
- Unicode characters in file path names cannot be handled by IBM Spectrum Protect Plus. All names must be in ASCII.
- The database table spaces, online logs, and the local database directory can be on one or separate dedicated logical volumes that are managed by either LVM2 or JFS2. For layout two examples, see the following pictures. In the first picture, two types of volume groups shown. In the second picture, all volumes for data and logs are on one volume group.




Figure 13. Logical volume layout examples




Figure 14. Single logical volume layout example

• Ensure that your Db2 logical volume setup does not include nested mount points.

### **Space requirements for Db2 protection**

Before you start backing up Db2 databases, ensure you have enough free disk space on the target and source hosts, and in the vSnap repository. Extra free disk space is required on the volume groups on the source host for creating temporary Logical Volume Manager (LVM) snapshots of the logical volumes that the Db2 database and log files are stored on. To create LVM snapshots of a protected Db2 database, ensure that the volume groups with Db2 data have sufficient free space.

#### LVM snapshots

LVM snapshots are point-in-time copies of LVM logical volumes. They are space-efficient snapshots with the changed data updates from the source logical volume. LVM snapshots are created in the same volume group as the source logical volume. The IBM Spectrum Protect Plus Db2 agent uses LVM snapshots to create a temporary, consistent point-in-time copy of the Db2 database.

The IBM Spectrum Protect Plus Db2 agent creates an LVM snapshot which is then mounted, and is copied to the vSnap repository. The duration of the file copy operation depends on the size of the Db2 database. During file copying, the Db2 application remains fully online. After the file copy operation finishes, the LVM snapshots are removed by the IBM Spectrum Protect Plus Db2 agent in a cleanup operation.

For AIX, no more than 15 snapshots can exist for each JFS2 file system. Internal and external JFS2 snapshots cannot exist at the same time for the same file system. Ensure that no internal snapshots exist on the JFS2 volumes as these snapshots can cause issues when the IBM Spectrum Protect Plus Db2 agent is creating external snapshots.

For every LVM or JFS2 snapshot logical volume containing data, allow at least 10 percent of its size as free disk space in the volume group. If the volume group has enough free disk space, the IBM Spectrum Protect Plus Db2 agent reserves up to 25 percent of the source logical volume size for the snapshot logical volume.

### LVM2 and JFS2

When you run a Db2 backup operation, Db2 requests a snapshot. This snapshot is created on a Logical Volume Management (LVM) system or a Journaled File System (JFS) for each logical volume with data or

logs for the selected database. In Linux systems, the logical volumes are managed by LVM2 with 1vm2 commands. On AIX, the logical volumes are managed by JFS2 and created with the JFS2 snapshot command as external snapshots.

A software-based LVM2 or JFS2 snapshot is taken as a new logical volume on the same volume group. The snapshot volumes are temporarily mounted on the same machine that runs the Db2 instance so that they can be transferred to the vSnap repository.

On the Linux operating system, the LVM2 volume manager stores the snapshot of a logical volume within the same volume group. On the AIX operating system, the JFS2 volume manager stores the snapshot of a logical volume within the same volume group. For both, there must be enough space on the machine to store the logical volume. The logical volume grows in size as data changes on the source volume while the snapshot exists. In multi-partitioned environments, when multiple partitions share the same volume, an extra snapshot of the volume is created for each partition. Ensure that the volume group has sufficient free space for the required snapshots.

### **Setting sudo privileges for Db2**

To use IBM Spectrum Protect Plus to protect your data, you must install the required version of the sudo program. For the Db2 application server, you must set up sudo in a specific way that might be different from other application servers.

### Before you begin

To determine the correct version of sudo to be installed, see technote 2013790.

#### **About this task**

Set up a dedicated IBM Spectrum Protect Plus agent user with the required superuser privileges for sudo. This configuration enables the agent user to run commands without a password.

#### **Procedure**

1. Create an application server user by issuing the following command:

```
useradd -m <agent>
```

where agent specifies the name of the IBM Spectrum Protect Plus agent user.

2. Set a password for the new user by issuing the following command:

```
passwd <agent>
```

3. To enable superuser privileges for the agent user, set the !requiretty setting. At the end of the sudo configuration file, add the following lines:

```
Defaults:<agent> !requiretty
<agent> ALL=(ALL) NOPASSWD:ALL
```

If your sudoers file is configured to import configurations from another directory, for example /etc/sudoers.d, you can add the lines in the appropriate file in that directory.

### Adding a Db2 application server

To start protecting your Db2 data, you must add the host address where your Db2 instances are located. You can repeat the procedure to add every host that you want to protect with IBM Spectrum Protect Plus. If your Db2 environment is multi-partitioned with multiple hosts, you must add each host to IBM Spectrum Protect Plus.

#### **About this task**

To add a Db2 application server to IBM Spectrum Protect Plus, you must have the host address of the machine.

#### **Procedure**

ı

- 1. In the navigation, expand Manage Protection > Applications > Db2.
- In the **Db2** window, click **Manage application servers**, and click **Add application server** to add the host machine.



Figure 15. Adding a Db2 agent

- 3. In the Application Properties section, enter the host address.
- 4. Choose to specify a user or use an SSH key.
  - If you selected to specify a user, either select an existing user or enter a user ID and password.
  - If you are using an SSH key, choose the key from the menu.

Note: The user must have sudo privileges set up.




Figure 16. Managing agent users

### Tip:

Db2 instances found are listed for each host. If your Db2 instance is partitioned, this information is listed with the host machine and the numbers of the partitions. For multi-host Database Partitioning Feature (DPF), the Db2 instance is displayed as a single unit.

5. Save the form, and repeat the steps to add other Db2 application servers to IBM Spectrum Protect Plus.

If your Db2 data is in a multi-partitioned environment with multiple hosts, you must add each host. Repeat the procedure for each Db2 host.

#### What to do next

After you add your Db2 application servers to IBM Spectrum Protect Plus, an inventory is automatically run on each application server to detect the relevant databases in those instances.

To verify that the databases are added, review the job log. Go to **Jobs and Operations**. Click the **Running Jobs** tab, and look for the latest Application Server Inventory log entry.

Completed jobs are shown on the **Job History** tab. You can use the **Sort By** list to sort jobs based on start time, type, status, job name, or duration. Use the **Search by name** field to search for jobs by name. You can use asterisks as wildcard characters in the name.

Databases must be detected to ensure that they can be protected. For instructions about running an inventory, see Detecting Db2 resources.

## **Detecting Db2 resources**

After you add IBM Db2 application servers to IBM Spectrum Protect Plus, an inventory to detect all Db2 instances and databases is run automatically. The inventory detects, lists, and stores all the Db2 databases for the selected host, and makes the databases available for protection with IBM Spectrum Protect Plus.

### Before you begin

Ensure that you added your Db2 application servers to IBM Spectrum Protect Plus. For instructions, see Adding a Db2 application server.

### **About this task**

Any Db2 partitions that are found in the inventory are listed for the Db2 instance. Partitions are listed by their partition number for each host appended to the host name in the **Instances** table.

#### **Procedure**

1. In the navigation pane, expand Manage Protection > Applications > Db2.

**Tip:** To add more Db2 instances to the **Instances** pane, follow the instructions in <u>Adding a Db2</u> application server.

2. Click Run Inventory.




Figure 17. Detecting Db2 resources

When the inventory is running, the button changes to show **Inventory In Progress**. You can run an inventory on any available application servers, but you can run only one inventory process at a time.

To view the job log, go to **Jobs and Operations**. Click the **Running Jobs** tab, and look for the latest Application Server Inventory log entry.

- Completed jobs are shown on the **Job History** tab. You can use the **Sort By** list to sort jobs based on start time, type, status, job name, or duration. Use the **Search by name** field to search for jobs by name. You can use asterisks as wildcard characters in the name.
- 3. Click on an instance to open a view that shows the databases that are detected for that instance. If any databases are missing from the **Instances** list, check your Db2 application server and rerun the inventory. In some cases, certain databases are marked as ineligible for backup; hover over the database to reveal the reason why.

**Tip:** To return to the list of instances, click the **Instances** hypertext in the **Backup Db2** pane.

#### What to do next

To start protecting Db2 databases that are cataloged in the selected instance, apply a service level agreement (SLA) policy to the instance. For instructions about setting an SLA policy, see <u>Defining an SLA policy</u>.

### **Testing the Db2 connection**

After you add a Db2 application server, you can test the connection. The test verifies communication with the server and the DNS settings between IBM Spectrum Protect Plus and the Db2 server. It also checks for the correct sudo permissions for the user.

#### **Procedure**

- 1. In the navigation pane, click Manage Protection > Applications > Db2.
- 2. In the **Db2** window, click **Manage Application Servers**, and select the **Host Address** you want to test. A list of the Db2 application servers that are available are shown.
- 3. Click **Actions** and choose **Test** to start the verification tests for physical, remote and operating system connections and settings.




Figure 18. Testing the connection

The test report shows a list of the tests. It consists of a test for the physical host network configuration, and tests for the remote server installation on the host, which checks SSH and SFTP on the host. The third test checks for operating system prerequisites and correct sudo privileges.

4. Click **OK** to close the test, and choose to rerun the test after you fix any failed tests.

### Backing up Db2 data

Define regular Db2 backup jobs with options to run and create backup copies to protect your data. You can enable continuous backing up of archive logs so that you can restore a point-in-time copy with rollforward options if required.

### Before you begin

During the initial backup, IBM Spectrum Protect Plus creates a new vSnap volume and NFS share. During incremental backups, the previously created volume is reused. The IBM Spectrum Protect Plus Db2 agent mounts the share on the Db2 server where the backup is to be completed.

Review the following procedures and considerations before you create a backup job definition:

- Add the application servers that you want to back up. For the procedure, see <u>Adding a Db2 application</u> server.
- Configure a Service Level Agreement (SLA) Policy. For the procedure, see <u>Defining a Service Level</u> Agreement backup job.

- Before an IBM Spectrum Protect Plus user can implement backup and restore operations, roles and
  resource groups must be assigned to the user. Grant users access to resources and backup and restore
  operations through the **Accounts** pane. For more information, see Managing user access.
- Inventory jobs should not be scheduled to run at the same time as backup jobs.
- Avoid configuring log backups for a single Db2 database with many backup jobs. If a single Db2 database is added to multiple job definitions with log backup enabled, a log backup from one job can truncate a log before it is backed up by the next job. This might cause point-in-time restore jobs to fail.

### **Procedure**

I

- 1. In the navigation menu, expand Manage Protection > Applications > Db2.
- 2. Select an instance or database for backing up by choosing one of the following actions:
  - Select an entire instance in the **Instances** pane by clicking the instance name check-box. Any databases added to this instance are automatically assigned to the SLA policy that you choose.
  - Select a specific database in an instance by clicking the instance name, and choosing a database from the list of databases in that instance.

Each item in the **Instances** pane is listed by instance or database name, the applied SLA policy, and the eligibility for log backup.

3. Click **Select Options** to enable or disable log backup, and to specify parallel streams to minimize time taken for large data movement in the backup operation. Click **Save** to commit the options.

Select **Enable Log Backup** to back up archive logs, which allows point-in-time restore options and recovery options. For Db2 log backup settings information, see Log backups.




Figure 19. Backup pane with the Enable Log Backup option

When you save the options, those options are used for all backup jobs for this database or instance as selected.

- 4. Select the database or instance again, and click **Select SLA Policy** to choose an SLA policy for that database or instance.
- 5. Save the SLA options.

To define a new SLA or to edit an existing policy with custom retention and frequency rates, select **Manage Protection** > **Policy Overview**. In the **SLA Policies** pane, click **Add SLA Policy**, and define your policy preferences.

### What to do next

When the SLA policy is saved, you can run an on-demand backup any time by clicking the policy **Actions** menu and selecting **Start**. The status in the log changes to show that the backup is Running.

### Defining a service level agreement backup job

After your Db2 databases are listed for each of your Db2 instances, select and apply a service level agreement (SLA) policy to start protecting your data.

#### **Procedure**

- 1. From the navigation menu, expand Manage Protection > Applications > Db2.
- 2. Select a Db2 instance to back up all the data in that instance, or click the instance name to view the databases available for backing up. You can then select individual databases in the Db2 instance that you want to back up.

Choose to backup an entire instance with all the data associated, or you can choose to backup one or more databases.




Figure 20. Db2 Backup pane showing instances




Figure 21. Db2 Backup pane showing databases in an instance

3. Click Select SLA Policy and choose an SLA policy, Gold, Silver, or Bronze. Save your choice.

Predefined choices of Gold, Silver, or Bronze, each have different frequencies and retention rates. You can create a custom SLA policy or edit an existing policy, by navigating to **Policy Overview** > **SLA Policies**.

4. Click **Select Options** to define options for your backup, such as enabling log backups for future recovery options, and specifying the parallel streams to reduce the time that is taken to back up large databases. Save your changes.




Figure 22. Backup options and SLA policies

5. Configure the SLA policy by clicking the icon in the **Policy Options** column of the **SLA Policy Status** table.

To read about more SLA configuration options, see <u>"Setting SLA configuration options for a backup</u> job" on page 140.

6. If you want to run the policy outside of the scheduled job, select the instance or database. Click **Actions** and select **Start**.

The status changes to **Running** for your chosen SLA and you can follow the progress of the job in the job log shown.



Figure 23. SLA policies

To pause the schedule of an SLA, click **Actions** and choose **Pause Schedule**.

To cancel a job after it has started, click **Actions** > **Cancel**.

### Setting SLA configuration options for a backup job

After you set up a service level agreement (SLA) for your backup job, you can choose to configure more options for that job. You can run scripts, exclude resources from the backup operation, and force a full base backup copy of a database if required.

#### **Procedure**

In the Policy Options column of the SLA Policy Status table for the job you are configuring, click the clipboard icon to specify extra configuration options.
 If the job is already configured, click on the icon to edit the configuration.




Figure 24. Specifying SLA configuration options

- 2. Click **Pre-Script** and define your pre-script configuration by choosing one of the following options:
  - Click **Use Script Server** and select an uploaded script from the menu.
  - Do not click **Use Script Server**. Select an application server from the list to run the script at that location.
- 3. Click **Post-Script** and define your post-script configuration by choosing one of the following options:
  - Click Use Script Server and select an uploaded script from the menu.
  - Do not click **Use Script Server**. Select an application server from the list to run the script at that location.

Scripts and script servers are configured on the **System Configuration** > **Script** page. For more information about working with scripts, see Configuring scripts.

4. To continue running the job when the script that is associated with the job fails, select **Continue job/** task on script error.

If this option is selected, the backup or restore operation is reattempted and the script task status is reported as COMPLETED when the script completes processing with a nonzero return code. If this option is not selected, the backup or restore is not reattempted and the script task status is reported as FAILED.

- 5. To exclude resources from a backup job, specify the resources to exclude from the job. Enter an exact resource name in the **Exclude Resources** field. If you are unsure of a name, use wildcard asterisks that are specified before the pattern (\*text\*) or after the pattern (text\*). Multiple wildcards can be entered with standard alphanumeric characters and the following special characters: \_ and \*. Separate entries with a semicolon.
- 6. To create a full new backup of a resource, enter the name of that resource in the **Force full backup of resources** field. Separate multiple resources with a semicolon.

The full backup creates a full new backup of that resource and replaces the existing backup of that resource for one occurrence only. After the full backup completes, the resource is backed up incrementally as before.

### Log backups

Archived logs for databases contain committed transaction data. This transaction data can be used to run a rollforward data recovery when you are running a restore operation. Using archive log backups enhances the recovery point objective for your data.

Ensure that you select the **Enable Log Backups** option to allow rollforward recovery when you set up a backup job or service level agreement (SLA) policy. When selected for the first time, you must run a backup job for the SLA policy to activate log archiving to IBM Spectrum Protect Plus on the database. This backup creates a separate volume on the vSnap repository, which is mounted persistently on the Db2 application server. The backup process updates either **LOGARCHMETH1** or **LOGARCHMETH2** parameters to point to that volume for log archiving purposes. The volume is kept mounted on the Db2 application server unless the **Enable Log Backup** option is cleared and a new backup job is run.

**Restriction:** In Db2 multi-partitioned environments, the **LOGARCHMETH** parameters across partitions must match.

When either **LOGARCHMETH1** or **LOGARCHMETH2** parameters are set with a value other than OFF, you can use archived logs for rollforward recovery. You can cancel log backup jobs at any time by clearing the **Enable Log Backups** option: go to **Manage Protection** > **Applications** > **Db2**, select the instance and click **Select Options**. This change takes effect after the next successful backup job completes, and the **LOGARCHMETH** parameter value is changed back to its original setting.

**Important:** IBM Spectrum Protect Plus can enable log backup jobs only when the **LOGARCHMETH1** parameter is set to LOGRETAIN or if one of the **LOGARCHMETH** parameters is set to OFF.

### If the LOGARCHMETH1 parameter is set to LOGRETAIN.

IBM Spectrum Protect Plus changes the **LOGARCHMETH1** parameter value to enable log backups.

If either LOGARCHMETH1 or LOGARCHMETH2 parameters are set to OFF and the other is set to DISK, TSM, or VENDOR.

IBM Spectrum Protect Plus uses the **LOGARCHMETH** parameter that is set to off to enable log backups.

### If both LOGARCHMETH parameters are set to DISK, TSM, or VENDOR.

This setting combination causes an error when IBM Spectrum Protect Plus attempts to enable log backups. To resolve the error, set one of the parameters to 0FF, and run the backup job with the **Enable Log Backups** option selected.

### Truncating archive log backups

IBM Spectrum Protect Plus automatically deletes older transactional logs after a successful database backup. This action ensures that the capacity of the log archive volume is not compromised by retention of older log files. These truncated log files are stored in the vSnap repository until the corresponding backup expires and is deleted. The retention of database backups is defined in the SLA policy that you select. For more information about SLA policies, see "Defining a service level agreement backup job" on page 138.

IBM Spectrum Protect Plus does not manage the retention of other archived log locations.

For more information about Db2 settings, see IBM Db2 Welcome page.

# **Restoring Db2 data**

To restore Db2 data from the vSnap repository, define a job that restores data from either the newest backup or an earlier backup copy. You can choose to restore data to the original instance or to an alternative instance on a different machine, and specify recovery options, and save the job.

### Before you begin

**Important:** For all restore operations, Db2 must be at the same version level on the source and target hosts. In addition to that requirement, you must ensure that an instance with the same name as the instance that is being restored exists on each host. This requirement applies when the target instance has the same name, and when the names are different. In order for the restore operation to succeed, both instances must be provisioned, one with original name and the other with the new name.

If your Db2 environment includes partitioned databases, the data of all partitions is backed up during regular backup jobs. All instances are listed in the backup pane. Multi-partitioned instances are shown with partition numbers and host names.

Before you create a restore job for Db2, ensure that the following requirements are met:

- At least one Db2 backup job is set up and running successfully. For instructions about setting up a backup job, see "Backing up Db2 data" on page 136.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is setting up the restore job. For more information about assigning roles, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

**Note:** When you are restoring multi-partitioned databases to an alternative location, ensure that the target instance is configured with the same partition numbers as the original instance. All of those partitions must be on a single host. When you are restoring data to a new instance that is renamed, both instances instances required for the restore operation must be configured with the same number of partitions.

Before you start a restore operation to an alternative instance, ensure that the file system structure on the source machine is matched on the target machine. This file system structure includes table spaces, online logs, and the local database directory. Ensure that dedicated volumes with sufficient space are allocated to the file system structure. Db2 must be at the same version level on the source and target hosts for all restore operations, and an instance of the same name must exist on each host. For more information about space requirements, see <a href="Space requirements for Db2">Space requirements for Db2 protection</a>. For more information about prerequisites and setup, see <a href="Prerequisites for Db2">Prerequisites for Db2</a>.

### **Procedure**

1. In the navigation pane, expand Manage Protection > Applications > Db2 and click Create Restore Job.

The Snapshot restore wizard opens.

2. Optional: If you started the restore wizard from the **Jobs and Operations** page, choose Db2 as the source type and click **Next**.

**Tip:** For a summary of your selections in the restore wizard, move the cursor to the information icon in the navigation pane of the wizard.

3. In the **Source select** page, click a Db2 instance to show the databases in that instance. Choose a database by clicking the plus icon beside the database name. Click **Next** to continue.

- 4. In the **Source snapshot** page, choose the type of restore operation required.
  - **On-Demand: Snapshot**: creates a once-off restore operation from a database snapshot. The job is not set to recur.
  - **On-Demand: Point in-Time**: creates a once-off restore operation from a point-in-time backup of the database. The job is not set to recur.
  - **Recurring**: creates a recurring job that runs on a schedule and repeats.

### Tip:

For an **On-Demand: Snapshot** you can select no recovery or to recover until the end of the backup. For an **On-Demand: Point in Time** restore job you can select to recover until the end of the available logs, or recover until a specific point-in-time.

5. In the same page, select a **Restore Location Type** as follows:

Location	Instructions
Site	Select this option to restore data from the primary or secondary site. Site is the only choice for on-demand point-in-time restore jobs.
Cloud Offload	Select this option to restore data from cloud storage. Specify the Restore Point to be used for the snapshot.
Repository Offload	Select this option to restore data from a vSnap repository. Specify the Restore Point to be used for the snapshot.
Cloud Archive	Select this option to restore data that is archived on the cloud. Specify the Restore Point to be used for the snapshot.
Repository Archive	Select this option to restore data that is archived in the vSnap repository. Specify the Restore Point to be used for the snapshot.

When you are creating an on-demand snapshot, you can specify a time-span in the snapshot that you are looking for. Where applicable you can use a different vSnap server for the operation.

6. Select a location for the restore operation. Choose one of the following location options, and click **Next**.

Option	Description
Demo	Select this option for restoring data from the demonstration vSnap server. This option is only available in certain setups.
Primary	Select this option to restore data from the primary vSnap server to the target destination. This location is available for restore location type Site.
Secondary	Select this option to restore data from the secondary vSnap server to the target destination. This location is available for restore location type Site.

Restore points are available from the **Restore Point** menu.

7. Choose a **restore method** appropriate for the destination chosen for the restore operation. Click **Next** to continue.

- **Instant Access**: In this mode, no further action is taken after IBM Spectrum Protect Plus mounts the volume from the vSnap repository. Use the data for custom recovery from the files in the mounted volume.
- **Production**: In this mode, the Db2 application server first copies the files from the vSnap repository volume to the target host, which is either an alternative location or the original instance. That copied data is then used to start the database.
- **Test**: In this mode, the agent creates a new database by using the data files directly from the vSnap repository.
- Add a database name when you are restoring the database to a different location and you want to rename the database.

### Tip:

Production is the only **restore method** that is available for restore operations to the original location. Any options not appropriate for the restore operation that you selected are not selectable.

To restore data to the original instance, follow the instructions in Restoring to the original instance. To restore data to an alternative instance, follow the instructions in Restoring to an alternate instance.

- 8. Set the destination for the restore operation by choosing one of the following options. Click **Next** to continue.
  - Restore to original instance: this option restores data to the original server and original instance.
  - **Restore to alternate instance**: this option restores data to a different specified location, creating a copy of the data at that location.

If you are restoring data to an alternative location, choose an instance in the **Instance** table before you click **Next**. The alternative instance must be on a different machine; unsuitable instances are not available for selection. For multi-partition databases, the target instance must have the same set of partitions on a single machine.

9. In the **Job Options** page, select the recovery, application, and advanced options for the restore operation you are defining.

#### Tip:

Recovery options are not available for instant access restore jobs.

- **No Recovery**. This option skips any rollforward recovery after the restore operation. The database remains in a Rollforward pending state until you decide whether you want to run the rollforward operation manually.
- **Recover until end of backup**. This option recovers the selected database to its state at the time the backup was created. The recovery process uses the log files that are included in the Db2 database backup.
- Recover until end of available logs. This option is available only if the logs are backed up in the
  Db2 backup job definition. IBM Spectrum Protect Plus uses the latest restore point. A temporary
  restore point for log backups is created automatically so that the Db2 database can be rolled
  forward to the end of the logs. This recovery option is not available if you selected a specific
  restore point from the list. This option is available only when you are running an on-demand pointin-time restore job which uses the latest backup.
- Recover until specific point-in-time. This option includes all the backup data up to a specific point-in-time. This option is available only if you enabled log backups in your Db2 backup job definition. Configure a point-in-time recovery by a specific date and time, for example, Jan 1, 2019 12:18:00 AM. IBM Spectrum Protect Plus finds the restore points directly before and after the selected point-in-time. During the recovery process, the older data backup volume and the newer log backup volume are mounted. If the point-in-time is after the last backup, a temporary restore point is created. This recovery option is not available if you selected a specific restore point from the list. This option is available only when you are running an on-demand point-in-time restore job that uses the newest backup.

Tip: To skip optional steps in the restore wizard, select Skip optional steps and click Next.

10. Optional: In the **Job Options** page, select the application options for the restore operation you are defining.

### Tip:

Application options are not available for instant access restore jobs.

• Overwrite existing databases. Choose this option to replace existing databases that have the same names during the restore recovery process. If this option is not selected, the restore job fails when databases with the same name are found during the restore operation. If you select this option, ensure that the Db2 log directory and the Db2 mirror log directory have no data.



**Attention:** Ensure that no other databases share the local database directory as the original database or that data is overwritten when this choice is selected.

- **Maximum Parallel Streams per Database**. You can choose to run the restore operation of data in parallel streams. This option is useful if you are restoring a large database.
- Specify the size of the Db2 database memory set in KB. Specify the memory, in KB, to be allocated for the database restore on the target machine. This value is used to modify the shared memory size of the Db2 database on the target server. To use the same shared memory size at both the source server and the target server, set the value to zero.
- 11. Optional: In the **Job Options** page, select the advanced options for the restore operation you are defining.
  - Run cleanup immediately on job failure. This option is selected by default to automatically clean up allocated resources as part of a restore operation when the recovery fails.
  - Continue with restores of other selected databases even if one fails. This option continues the restore operation if one database in the instance fails to be restored successfully. The process continues for all other databases that are being restored. When this option is not selected, the restore job stops when the recovery of a resource fails.
  - **Mount point prefix**. For instant access restore operations, specify the prefix for the path where the mount point is to be directed.
- 12. Choose script options in the **Apply Scripts** page, and click **Next** to continue.
  - Select **Pre-Script** to select an uploaded script, and an application or script server where the prescript runs. To select an application server where the script runs, clear the **Use Script Server** check box. Go to the **System Configuration** > **Script** page to configure scripts and script servers.
  - Select **Post-Script** to select an uploaded script and an application or script server where the postscript runs. To select an application server where the script runs, clear the **Use Script Server** check box. Go to the **System Configuration** > **Script** page to configure scripts and script servers.
  - Select **Continue job/task on script error** to continue running the job when the script that is associated with the job fails. When this option is enabled and the prescript completes with a nonzero return code, the backup or restore job continues to run and the prescript task status returns COMPLETED. If a postscript completes with a nonzero return code, the postscript task status returns COMPLETED. When this option is not selected, the backup or restore job does not run, and the prescript or postscript task status returns with a FAILED status.
- 13. In the **Schedule** page, name the restore job and choose the frequency for the job to run. Schedule the start time, and click **Next** to continue.
  - If the restore job you are specifying is an on-demand job, there is no option to enter a schedule. Specify a schedule only for recurrent restore jobs.
- 14. In the **Review** page, review your selections for the restore job. If all the details are correct for your restore job, click **Submit**, or click **Back** to make amendments.

#### Results

A few moments after you click **Submit**, the **onDemandRestore** record is added to the **Job Sessions** pane. To view progress of the restore operation, expand the job. You can also download the log file by clicking

the download icon . All running jobs are viewable in the **Jobs and Operations Running Jobs** page.

To restore data to the original instance, follow the instructions in Restoring to the original instance. To restore data to an alternative instance, follow the instructions in Restoring to an alternate instance.

### Restoring Db2 data to the original instance

You can restore a database backup to its original instance on the original host. You can restore to the latest backup or an earlier Db2 database backup version. When you restore a database to its original instance, you cannot rename it. This restore option runs a full production restoration of data, and existing data is overwritten at the target site if the **Overwrite existing databases** option is selected.

### Before you begin

If your Db2 environment includes partitioned databases, the data of all partitions is backed up during regular backup jobs. All instances are listed in the backup pane. Multi-partitioned instances are shown with partition numbers and host names.

Before you create a restore job for Db2, ensure that the following requirements are met:

- At least one Db2 backup job is set up and running successfully. For instructions about setting up a backup job, see "Backing up Db2 data" on page 136.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is setting up the restore job. For more information about assigning roles, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

### **Procedure**

In the navigation pane, expand Manage Protection > Applications > Db2 and click Create Restore
Job.

The Snapshot restore wizard opens.

2. Optional: If you started the restore wizard from the **Jobs and Operations** page, choose Db2 as the source type and click **Next**.

**Tip:** For a summary of your selections in the restore wizard, move the cursor to the information icon in the navigation pane of the wizard.

- 3. In the **Source select** page, click a Db2 instance to show the databases in that instance. Choose a database by clicking the plus icon beside the database name. Click **Next** to continue.
- 4. In the **Source snapshot** page, choose the type of restore operation required.
  - **On-Demand: Snapshot**: creates a once-off restore operation from a database snapshot. The job is not set to recur.
  - **On-Demand: Point in-Time**: creates a once-off restore operation from a point-in-time backup of the database. The job is not set to recur.
  - **Recurring**: creates a recurring job that runs on a schedule and repeats.

### Tip:

For an **On-Demand: Snapshot** you can select no recovery or to recover until the end of the backup. For an **On-Demand: Point in Time** restore job you can select to recover until the end of the available logs, or recover until a specific point-in-time.

5. In the same page, select a **Restore Location Type** as follows:

Location	Instructions
Site	Select this option to restore data from the primary or secondary site. Site is the only choice for on-demand point-in-time restore jobs.
Cloud Offload	Select this option to restore data from cloud storage. Specify the Restore Point to be used for the snapshot.
Repository Offload	Select this option to restore data from a vSnap repository. Specify the Restore Point to be used for the snapshot.
Cloud Archive	Select this option to restore data that is archived on the cloud. Specify the Restore Point to be used for the snapshot.
Repository Archive	Select this option to restore data that is archived in the vSnap repository. Specify the Restore Point to be used for the snapshot.

When you are creating an on-demand snapshot, you can specify a time-span in the snapshot that you are looking for. Where applicable you can use a different vSnap server for the operation.

Select a location for the restore operation. Choose one of the following location options, and click Next.

CAL.	
Option	Description
Demo	Select this option for restoring data from the demonstration vSnap server. This option is only available in certain setups.
Primary	Select this option to restore data from the primary vSnap server to the target destination. This location is available for restore location type Site.
Secondary	Select this option to restore data from the secondary vSnap server to the target destination. This location is available for restore location type Site.

Restore points are available from the **Restore Point** menu.

7. In the **Restore Method** page, choose **Production** for the restore operation.

In **Production** mode, the Db2 application server first copies the files from the vSnap repository volume to the target host. That copied data is then used to start the database.

**Tip:** Avoid entering a new database name when you are restoring a production operation to the original instance as it will not be implemented.

- 8. Set the destination for the restore operation to **Restore to original instance** to restore data to the original server. Click **Next** to continue.
- 9. Choose options as described in "Restoring Db2 data" on page 142.
- 10. In the **Schedule** page, name the restore job and choose the frequency for the job to run. Schedule the start time, and click **Next** to continue.
  - If the restore job you are specifying is an on-demand job, there is no option to enter a schedule. Specify a schedule only for recurrent restore jobs.
- 11. In the **Review** page, review your selections for the restore job. If all the details are correct for your restore job, click **Submit**, or click **Back** to make amendments.

#### Results

A few moments after you click **Submit**, the **onDemandRestore** record is added to the **Job Sessions** pane. To view progress of the restore operation, expand the job. You can also download the log file by clicking



the download icon . All running jobs are viewable in the **Jobs and Operations Running Jobs** page.

## Restoring Db2 databases to an alternative instance

You can restore a Db2 database to another Db2 instance on an alternative host. You can also choose to restore a database to an instance with a different name and rename the database. This process creates an exact copy of the database on a different host in a different instance. If you are restoring a resource to an alternative location, you can restore the same resource multiple times without specifying different target hosts.

## Before you begin

Important: For all restore operations, Db2 must be at the same version level on the source and target hosts. In addition to that requirement, you must ensure that an instance with the same name as the instance that is being restored exists on each host. This requirement applies when the target instance has the same name, and when the names are different. In order for the restore operation to succeed, both instances must be provisioned, one with original name and the other with the new name.

Before you create a restore job for Db2, ensure that the following requirements are met:

- At least one Db2 backup job is set up and running successfully. For instructions about setting up a backup job, see "Backing up Db2 data" on page 136.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is setting up the restore job. For more information about assigning roles, see Chapter 13, "Managing user access," on page 275.
- · When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

Before you start a restore operation to an alternative instance, ensure that the file system structure on the source machine is matched on the target machine. This file system structure includes table spaces, online logs, and the local database directory. Ensure that dedicated volumes with sufficient space are allocated to the file system structure. Db2 must be at the same version level on the source and target hosts for all restore operations, and an instance of the same name must exist on each host. For more information about space requirements, see Space requirements for Db2 protection. For more information about prerequisites and setup, see Prerequisites for Db2.

Restriction: If data exists on the local database directory to which you are restoring the database backup to, and the Overwrite existing databases option is not selected, the restore operation fails. No other data can share the local database directory where the backup is restored. When the Overwrite existing databases option is selected, any existing data is removed and the local database directory on the alternative host.

Note: When you are restoring multi-partitioned databases to an alternative location, ensure that the target instance is configured with the same partition numbers as the original instance. All of those partitions must be on a single host. When you are restoring data to a new instance that is renamed, both instances instances required for the restore operation must be configured with the same number of partitions.

#### **About this task**

Ensure that the disk paths for the redirected restore operation include the instance name and the database name. The information is needed for all types of paths: database paths, container paths, storage paths, and log and mirror log paths.

#### **Procedure**

1. In the navigation pane, expand **Manage Protection > Applications > Db2** and click **Create Restore Job**.

The Snapshot restore wizard opens.

2. Optional: If you started the restore wizard from the **Jobs and Operations** page, choose Db2 as the source type and click **Next**.

**Tip:** For a summary of your selections in the restore wizard, move the cursor to the information icon in the navigation pane of the wizard.

- 3. In the **Source select** page, click a Db2 instance to show the databases in that instance. Choose a database by clicking the plus icon beside the database name. Click **Next** to continue.
- 4. In the **Source snapshot** page, choose the type of restore operation required.
  - **On-Demand: Snapshot**: creates a once-off restore operation from a database snapshot. The job is not set to recur.
  - **On-Demand: Point in-Time**: creates a once-off restore operation from a point-in-time backup of the database. The job is not set to recur.
  - **Recurring**: creates a recurring job that runs on a schedule and repeats.

## Tip:

For an **On-Demand: Snapshot** you can select no recovery or to recover until the end of the backup. For an **On-Demand: Point in Time** restore job you can select to recover until the end of the available logs, or recover until a specific point-in-time.

5. In the same page, select a **Restore Location Type** as follows:

Location	Instructions
Site	Select this option to restore data from the primary or secondary site. Site is the only choice for on-demand point-in-time restore jobs.
Cloud Offload	Select this option to restore data from cloud storage. Specify the Restore Point to be used for the snapshot.
Repository Offload	Select this option to restore data from a vSnap repository. Specify the Restore Point to be used for the snapshot.
Cloud Archive	Select this option to restore data that is archived on the cloud. Specify the Restore Point to be used for the snapshot.
Repository Archive	Select this option to restore data that is archived in the vSnap repository. Specify the Restore Point to be used for the snapshot.

When you are creating an on-demand snapshot, you can specify a time-span in the snapshot that you are looking for. Where applicable you can use a different vSnap server for the operation.

6. Select a location for the restore operation. Choose one of the following location options, and click **Next**.

Option	Description
Demo	Select this option for restoring data from the demonstration vSnap server. This option is only available in certain setups.

Option	Description
Primary	Select this option to restore data from the primary vSnap server to the target destination. This location is available for restore location type Site.
Secondary	Select this option to restore data from the secondary vSnap server to the target destination. This location is available for restore location type Site.

Restore points are available from the Restore Point menu.

- 7. Choose a restore method appropriate for the destination chosen for the restore operation. Click Next to continue.
  - **Production**: In this mode, the Db2 application server first copies the files from the vSnap repository volume to the target host, which is either an alternative location or the original instance. That copied data is then used to start the database.
  - Test: In this mode, the agent creates a new database by using the data files directly from the vSnap repository.
  - Instant Access: In this mode, no further action is taken after IBM Spectrum Protect Plus mounts the volume from the vSnap repository. Use the data for custom recovery from the files in the
  - Add a database name when you are restoring the database to a different location and you want to rename the database.
- 8. Set the destination for the restore operation to **Restore to alternate instance** to restore data to a different location, which you can select from the list of eligible locations. Click Next to continue.
  - When you are restoring to an alternative location, choose an instance in the **Instance** table before you click **Next**. Unsuitable target instances cannot be selected.
- 9. Choose options as described in "Restoring Db2 data" on page 142.
- 10. In the Schedule page, name the restore job and choose the frequency for the job to run. Schedule the start time, and click Next to continue.
  - If the restore job you are specifying is an on-demand job, there is no option to enter a schedule. Specify a schedule only for recurrent restore jobs.
- 11. In the **Review** page, review your selections for the restore job. If all the details are correct for your restore job, click **Submit**, or click **Back** to make amendments.

### **Results**

A few moments after you click **Submit**, the **onDemandRestore** record is added to the **Job Sessions** pane. To view progress of the restore operation, expand the job. You can also download the log file by clicking



the download icon . All running jobs are viewable in the **Jobs and Operations Running Jobs** page.

# **Exchange Server**

After you successfully register an Exchange application server, you can start to protect Microsoft Exchange data with IBM Spectrum Protect Plus. Define a service level agreement (SLA) policy to create backup jobs with specific schedules, retention policies, and scripts.

## **Prerequisites for Exchange Server**

Ensure that all prerequisites for your Microsoft Exchange application are met before you start protecting Microsoft Exchange databases with IBM Spectrum Protect Plus.

For more information, see "Microsoft Exchange Server requirements" on page 26.

### Virtualization support

IBM Spectrum Protect Plus supports Microsoft Exchange Server running on a physical (bare metal) server, as well as in a virtualization environment. The following virtualization environments are supported:

- VMware ESX guest operating system
- Microsoft Windows Hyper-V guest operating system

# **Privileges**

To help ensure that a Microsoft Exchange agent can work in your IBM Spectrum Protect Plus environment, you must set up the appropriate privileges for the Exchange user account.

#### Role-based access control

You are required to register the Exchange Server with IBM Spectrum Protect Plus with an Exchange user that has local administrator privileges and the correct role-based access control (RBAC) permissions.

Also, for granular restore operations you are required to use an Exchange user that has local administrator privileges and the correct RBAC permissions.

Minimum requirements for the Exchange user:

1. Verify that the Exchange user is a member of a local Administrator group and has an active Exchange mailbox in the domain.

By default, Windows adds the Exchange Organization Administrators group to other security groups, including the local Administrators group. For Exchange users who are not members of the Exchange Organization Management group, you must manually add the user account to the local Administrators group:

- On the computer of the domain member, click **Administrative tools** > **Computer Management** > **Local Users and Groups tool**.
- On a domain controller computer that does not have a local Administrators group or Local Users and Groups tool, manually add the user account to the Administrators group in the domain: Click Administrative tools > Active Directory Users and Computers tool.
- 2. Set the role and scope.
  - Verify that the Exchange user has the correct RBAC permissions.

You must assign the following management roles to each Exchange user that does mailbox restore operations:

- Active Directory Permissions
- ApplicationImpersonation
- Databases
- Disaster Recovery
- Mailbox Import Export

- Public Folders
- View-Only Configuration
- View-Only Recipients

Place users that you want to do mailbox restore tasks into an Exchange Server role group that contains these roles.

Exchange Server includes several built-in role groups. The Organization Management role group by default contains most, if not all of the roles that are listed.

Place the user that you want to do mailbox restore tasks into the Organization Management role group (ensuring it contains all of the listed roles).

Alternatively, you can place the user into another role group that you created or any other built-in role group that contains the roles that are listed.

**Note:** A user whose name is not in the Exchange Organization Management role group or subgroups might experience slower performance when they are completing restore operations.

**Important:** You can manage Exchange role groups by using the Exchange Admin Center (EAC) or Exchange Powershell Cmdlets **only** if your user name is authorized by the security policy in your organization.

Management Role Scope

Ensure that the following Exchange objects are in the management role scope for the Exchange user:

- The Exchange Server that contains the required data.
- The recovery database that is created by IBM Spectrum Protect Plus.
- The database that contains the active mailbox.
- The database that contains the active mailbox of the user who completes the restore operation.

### **Encrypting File System**

IBM Spectrum Protect Plus for Exchange requires that Encrypting File System (EFS) is enabled in the local or group domain policy, and a valid Domain Data Recovery Agent (DRA) certificate is available. If a custom group policy is defined and linked to the organizational unit, ensure that the Exchange server is part of the organizational unit.

### **Exchange certificates**

Exchange digital certificates must be installed and configured for the mailbox browser to function during a granular restore operation. Ensure that the current Exchange certificates are installed and configured correctly in your environment.

**Note:** With Exchange 2016 and Exchange 2019, by default the Exchange Server is configured to use Transport Layer Security (TLS). This TLS security encrypts communication between internal Exchange servers, and between Exchange services on the local server.

## Adding an Exchange application server

When you register Microsoft Exchange Server, an inventory of Exchange databases is added to IBM Spectrum Protect Plus. When the inventory is available, you can start to backup and restore your Exchange databases and run reports.

### **About this task**

To register a Microsoft Exchange application server, you need the IP address or host name.

#### **Procedure**

To add a Microsoft Exchange application server, complete the following steps:

- 1. In the navigation pane, expand Manage Protection > Applications > Exchange.
- 2. On the **Exchange** page, click **Manage Application Servers**, and then click **Add Application Server** to add the host system.
- 3. In the **Application Properties** form, enter the IP or host address.
- 4. Enter a user ID in the format of active directory domain and user account (domain\user), and the associated password. This user must have the correct Exchange roles and privileges. For more information about Exchange privileges, see "Privileges" on page 151.
- 5. Click **Save**, and repeat the steps to add other Microsoft Exchange instances to IBM Spectrum Protect Plus.

**Important:** In a database availability group (DAG) environment, register all Microsoft Exchange application servers in the DAG.

#### What to do next

ı

When you add your Exchange application server to IBM Spectrum Protect Plus, an inventory is automatically run on each instance. Databases must be detected to ensure that they can be backed up, and you can run a manual inventory at any time to detect updates. For instructions about running a manual inventory, see "Detecting Exchange databases by running an inventory" on page 153. For instructions about setting up Exchange database backup jobs, see "Defining a Service Level Agreement backup job" on page 154.

## Detecting Exchange databases by running an inventory

When you add your Microsoft Exchange Server instances to IBM Spectrum Protect Plus, an inventory is run automatically. However, you can run an inventory on an Exchange application server manually at any time to detect updates and list all of the Exchange databases for each instance.

## Before you begin

Ensure that you added your Exchange instances to IBM Spectrum Protect Plus. For instructions about adding an Exchange instance, see "Adding an Exchange application server" on page 152.

### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > Exchange.
- 2. Click Run Inventory.
  - When the inventory is running, the button label changes to **Inventory In Progress**. You can run an inventory on any available application server, but you can run only one inventory process at a time.
- 3. To monitor the inventory job, go to **Jobs and Operations**. Click the **Running Jobs** tab, and look for the latest Application Server Inventory log entry.
  - Completed jobs are shown on the **Job History** tab. You can use the **Sort By** list to sort jobs based on start time, type, status, job name, or duration. Use the **Search by name** field to search for jobs by name. You can use asterisks as wildcard characters in the name.
- 4. When the inventory job is complete, on the **Exchange Backup** pane, click an Exchange instance to open a view that shows the databases that are detected for that instance. If any databases are missing from the **Instances** list, check your Microsoft Exchange application server and rerun the inventory.

**Tip:** To return to the list of instances, click the **Instances** hypertext in the Exchange Backup pane.

### **Testing the Exchange Server connection**

After you register a Microsoft Exchange application server and add it to the application server list, test the connection. The test verifies communication between IBM Spectrum Protect Plus and the host application server.

#### **Procedure**

1. In the navigation pane, expand Manage Protection > Applications > Exchange.

2. On the Exchange page, click Manage Application Servers.

The Microsoft Exchange application servers that are available are shown.

3. Click **Actions** for the Microsoft Exchange application server that you want to test, and then click **Test**.

The test report shows you a list of the tests that ran and their status. Each test procedure includes a test of the physical host network configuration, a remote session test, and a test of Windows prerequisites such as user administrator privileges.

4. Click **OK** to close the test. Run the test again after you fix any issues.

## **Backing up Exchange databases**

To protect Microsoft Exchange databases, you can define a backup job that runs continuously to create incremental backups. You can also run on-demand backup jobs outside of the schedule.

## Before you begin

Ensure that the application servers that contain the Exchange databases you want to back up are added. For more information, see "Adding an Exchange application server" on page 152.

#### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > Exchange.
- 2. On the **Exchange Backup** pane, click the Microsoft Exchange instance, and then select the database to back up.

Each database is listed by instance or database name, the applied SLA policy, and the eligibility for log backup.

3. Click Run.

The backup job begins, and you can view the details in **Jobs and Operation > Running Jobs**.

**Tip:** The **Run** button is only enabled for a single database backup, and the database must have an SLA policy applied.

4. To run backup jobs for multiple databases, select the databases in the Exchange backup pane, and click **Select an SLA Policy**.

For more information about defining SLA policy backup jobs, and backup job options, see <u>"Defining a Service Level Agreement backup job"</u> on page 154.

## Defining a Service Level Agreement backup job

When your Microsoft Exchange databases are listed for each of your Exchange instances, select and apply a service level agreement (SLA) policy to start protecting your data.

#### **About this task**

IBM Spectrum Protect Plus supports single or multiple Microsoft Exchange databases per Exchange backup job. Multiple database backup jobs run sequentially.

#### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > Exchange.
- 2. Select an Exchange instance to back up all the data in that instance, or click an instance name, and then select individual databases that you want to back up.
- 3. Click **Select an SLA Policy** and choose an SLA Policy.
  - Predefined choices are Gold, Silver, and Bronze, each with different frequencies and retention rates. Gold is the most frequent with the shortest retention rate. You can also create a custom SLA policy or edit an existing policy. For more information see "Creating an SLA policy" on page 87.
- 4. Click **Select Options** to define options for your backup, such as enabling log backups for future recovery options, and specifying the parallel streams to reduce the time that is taken to back up large databases. Save your changes.

- 5. Configure the SLA policy by clicking the icon in the **Policy Options** column of the **SLA Policy Status** table.
  - For more information about SLA configuration options, see <u>"Setting SLA configuration options for a backup job"</u> on page 155.
- 6. To run the policy outside of the scheduled job, select the instance or database and then click **Actions** > **Start**.

The status changes to **Running** for your chosen SLA. To pause the schedule, click **Actions** > **Pause Schedule**, and to cancel a job after it has started, click **Actions** > **Cancel**.

### Setting SLA configuration options for a backup job

After you set up a service level agreement (SLA) for your backup job, you can choose to configure more options for that job. Extra SLA options include running scripts, excluding resources from the backup operation, and forcing a full base backup copy if required.

#### **Procedure**

- 1. In the **Policy Options** column of the **SLA Policy Status** table for the job that you are configuring, click the clipboard icon to specify additional configuration options.
- 2. To define a pre-script configuration, select **Pre-Script** and take one of the following actions:
  - To use a script server, select **Use Script Server** and choose an uploaded script from the **Script** or **Script Server** list.
  - To run a script on an application server, clear the **Use Script Server** check box, and choose an application server from the **Application Server** list.
- 3. To define a post-script configuration, select **Post-Script** and take one of the following actions:
  - To use a script server, select **Use Script Server** and choose an uploaded script from the **Script** or **Script Server** list.
  - To run a script on an application server, clear the **Use Script Server** check box, and choose an application server from the **Application Server** list.
  - Scripts and script servers are configured on the **System Configuration** > **Script** page. For more information about working with scripts, see Configuring scripts.
- 4. Select **Continue job/task on script error** to continue running the job when the script that is associated with the job fails.
  - If this option is selected, the backup or restore operation is attempted and the script task status is reported as COMPLETED when the script completes processing with a nonzero return code. If this option is not selected, the backup or restore is not attempted and the script task status is reported as FAILED.
- 5. Specify resources to exclude them from the backup job. Enter an exact resource name in the **Exclude Resources** field. If you are unsure of a name, use wildcard asterisks that are specified before the pattern (\*text\*) or after the pattern (text\*). Multiple wildcards can be entered with standard alphanumeric characters and the following special characters: \_ and \*. Separate entries with a semicolon.
- 6. If you want to create a full backup of a particular resource, enter the name of that resource in the **Force full backup of resources** field. Separate multiple resources with a semicolon.
  - A full backup replaces the existing backup of that resource for one occurrence only. After that, the resource is backed up incrementally as before.
- 7. Click Save.

### **Backing up Exchange database logs**

You can back up the database transaction logs for Microsoft Exchange databases. Exchange log backups are scheduled by using Windows Task Scheduler. When log backups are available, you can run a

rollforward data recovery during a restore operation to ensure that the data is recovered to the latest possible point in time.

#### **About this task**

When log backups are enabled, a Task Scheduler task is created on the Exchange server. The task runs a backup operation of your Exchange log files according to the SLA policy.

### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > Exchange.
- 2. Click the Microsoft Exchange instance that you want to protect, and then select the databases whose logs you want to back up.

**Tip:** The **Eligible for Log Backup** column shows the databases for which you can run log backups. If a database is registered as not eligible for log backup, a hover help explanation is provided.

- 3. Click **Select Options** and then select **Enable Log Backup**.
- 4. Enter the frequency of the log backups in days, hours, or minutes.
- 5. Choose the start date and select the time for the log backups to begin, and then click **Save**.

#### Results

The database transaction logs are backed up to the vSnap server according to the selected frequency.

**Restriction:** The database logs are backed up on the preferred node only. Only one Microsoft Exchange instance at a time can write log backups to the vSnap server.

Any log backup issues that occur are displayed in the Alert notifications in IBM Spectrum Protect Plus.

## Backing up Exchange databases in a Database Availability Group

You can back up the mailbox databases in a Microsoft Exchange Database Availability Group (DAG) and specify whether to use the active copy or a passive copy of the database for the backup. The Exchange servers in a DAG environment synchronize the data between active and passive copies for high availability.

#### About this task

By using the information from an inventory job, IBM Spectrum Protect Plus provides a DAG view that displays all of the databases in an Exchange DAG environment. Each database has an active copy on one server in the DAG, and one or more passive copies on the other servers. By default, scheduled backups are taken from the server that the database is active on, but you can select a different server to back up a passive copy of the database.

### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > Exchange.
- 2. In the Exchange Backup pane, click the View menu and select Database Availability Groups.
- 3. Click the Microsoft Exchange DAG that you want to view, and then select the databases to back up.
- 4. Click **Select Options**. In the **Backup preferred node** list, select the instance to run the backups on. With the **Backup preferred node** option, you can select a passive copy of the database for the backup.
- 5. Click **Select an SLA Policy** and then select an SLA policy from the list.
- 6. To create the job definition by using default options, click Save.
  The DAG databases are scheduled for backup jobs in accordance with the selected SLA policies and the preferred node choices.
- To run the selected policy outside of the schedule, in the SLA Policy Status pane, click Actions > Start.

## **Incremental forever backup strategy**

IBM Spectrum Protect Plus provides a backup strategy called *incremental forever*. Rather than scheduling periodic full backup jobs, this backup solution requires only one initial full backup. Afterward, an ongoing sequence of incremental backup jobs occurs.

The incremental forever backup solution provides the following advantages:

- Reduces the amount of data that goes across the network
- Reduces data growth because all incremental backups contain only the blocks that changed since the previous backup
- Reduces the duration of backup jobs

The IBM Spectrum Protect Plus incremental forever process includes the following steps:

- 1. The first backup job creates a VSS snapshot of the Exchange application. As a result, the database files are in an application consistent state. The complete database files are copied to the vSnap location.
- 2. All subsequent backups create a VSS snapshot of the Exchange application. The database files are in an application consistent state. However, only the change blocks of the database files are copied to the vSnap location.
- 3. The backups are reconstructed at each point in time that a backup is performed, making it possible to recover the database from any single backup point.

# Restoring Exchange databases

If data in a Microsoft Exchange database is lost or corrupted, you can restore the data from a backup copy. Use the "Snapshot restore" wizard to set up a restore job schedule or an on-demand restore operation. You can define a job that restores data to the original instance or to an alternative instance, with different types of recovery options and configurations available.

#### Before you begin

Ensure that the following requirements are met:

- At least one Microsoft Exchange backup job is defined and ran successfully. For instructions about defining a backup job, see "Defining a Service Level Agreement backup job" on page 154.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is defining the restore job. For more information about assigning roles, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

**Important:** For granular restore operations, you must log on to the Exchange application server and use the Microsoft Management Console (MMC) GUI to complete mailbox batch restore and mailbox restore browser tasks.

### **Procedure**

To restore data in a Microsoft Exchange database, take one of the following actions:

- Restore a database to the original instance and location.
- Restore a database to the original instance with a different file location.
- Restore a database to an alternative instance.
- Restore mailbox data by using the granular restore function.
- Restore a database in a database availability group (DAG).

### Restoring an Exchange database to the original instance

Restore a Microsoft Exchange database to its original instance by using production mode or test mode. Choose between restoring the latest backup or an earlier Exchange database backup version.

### Before you begin

Ensure that the following requirements are met:

- At least one Microsoft Exchange backup job is defined and ran successfully.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is defining the restore job. For more information about assigning roles, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275.

#### **About this task**

When you restore a database to its original location in production mode, you cannot rename it. This restore option runs a full production restore operation, and existing data is overwritten at the target site.

#### **Procedure**

To define an Exchange restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Applications** > **Exchange** > **Create Restore Job** to open the "Snapshot restore" wizard.

## Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore
   Job > Exchange.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the plus icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.

The selected sources are added to the restore list next to the database list. To remove an item from the list, click the minus icon next to the item.

- c) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Restore Type	Select the type of restore job:
	On-Demand: Snapshot Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-Demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring  Creates a repeating point-in-time restore job that runs on a schedule.

Option	Description
Restore Location Type	Select a type of location from which to restore data:
Турс	The site where snapshots were backed up. The site is defined on the <b>System</b> Configuration > Site pane.
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	<b>Demo</b> The demonstration site from which to restore snapshots.
	Primary  The primary site location from which to restore snapshots.
	Secondary The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

- 4. On the **Set destination** page, select **Restore to original instance** and click **Next**.
- 5. On the **Restore method** page, choose from the following options:
  - **Test**. In test mode, the agent creates a new database by using the data files directly from the vSnap repository. This restore type might be used for testing purposes.
  - **Production**. In production mode, the agent first restores the files from the vSnap volume back to primary storage and then creates the new database by using the restored files.

For Test restore only, in the **New Database Name** field, enter the new name for the restored database. The **New Database Name** field is also displayed when you choose Production restore, but this is for restoring to a new database location on the original instance. For detailed instructions on this task, see "Restoring an Exchange database to a new location on the original instance" on page 161.

6. Optional: On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

### **Recovery Options**

Choose from the following recovery options:

### No Recovery

This option skips any rollforward recovery after the restore operation. The database remains in a Rollforward pending state until you decide whether you want to run the rollforward recovery manually.

### Recover until end of backup

Restore the selected database to the state at the time the backup was created.

### Recover until end of available logs

This option restores the database and applies all available logs (including logs newer than the backup that might exist on the application server) to recover the database up to the latest possible time. This option is available only if you selected **Enable Log Backup** in the backup iob.

### Recover until specific point in time

When log backups are enabled, this option restores the database and applies logs from the log backup volume to recover the database up to an intermediate, user-specified point in time. Choose the date and time by selecting from the **By Time** options.

## **Application Options**

Set the application options:

### **Maximum Parallel Streams per Database**

Set the maximum data stream from the backup storage per database. This setting applies to each database in the job definition. Multiple databases can still be restored in parallel if the value of the option is set to 1. Multiple parallel streams might improve restore speed, but high-bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring an Exchange database to its original location by using its original database name.

## **Advanced Options**

Set the advanced job definition options:

### Run cleanup immediately on job failure

Enable this option to automatically clean up allocated resources as part of a restore if the recovery fails.

- 7. Optional: On the **Apply scripts** page, select the **Pre-Script** or **Post-Script** to apply, or choose **Continue job/task on script error**. For more information about working with scripts, see <u>Configuring scripts</u>. Click **Next** to continue.
- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

The restore job is created, and you can check on its status in **Jobs and Operations > Running Jobs**.

### Restoring an Exchange database to a new location on the original instance

You can restore an Exchange database to its original instance, but to a new location on the application server. Choose between restoring the latest backup or an earlier Exchange database backup version.

#### **About this task**

When you restore a database to its original instance by using a production restore operation, you can restore the database to a new file location on the application server with a new name for the restored database. In production mode, the agent first restores the files from the vSnap volume back to primary storage and then creates a new database by using the restored files.

#### **Procedure**

To define an Exchange restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Applications** > **Exchange** > **Create Restore Job** to open the "Snapshot restore" wizard.

## Tips:

- You can also open the "Snapshot restore" wizard by clicking **Jobs and Operations** > **Create Restore Job** > **Exchange**.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the plus icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.

The selected sources are added to the restore list next to the database list. To remove an item from the list, click the minus icon next to the item.

- c) Click **Next** to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Restore Type	Select the type of restore job:
	On-Demand: Snapshot Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-Demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring  Creates a repeating point-in-time restore job that runs on a schedule.
Restore Location Type	Select a type of location from which to restore data:  Site  The site where snapshots were backed up. The site is defined on the System Configuration > Site pane.

Option	Description
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	<b>Demo</b> The demonstration site from which to restore snapshots.
	Primary  The primary site location from which to restore snapshots.
	Secondary The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

- 4. On the **Set destination** page, select **Restore to original instance** and click **Next**.
- 5. In the **Restore Method** page, click the **Production** restore option.

**Tip:** It is mandatory to select Production mode for this restore operation.

- a) In the **Name** field, expand the database name to see the path information for the existing database on the application server.
- b) In the **New Database Name** field, enter the new name for the restored database.
- c) In the **Destination Path** field, enter the new directory location for the database file on the server, including the .edb name, and the logs location.



**Warning:** The destination directories that you enter in the **Destination Path** field must already exist on the application host. If not, then create the necessary directories on the server before you complete the restore operation.

For example, for a database that is named Database\_A, enter C:\<new\_destination\_path>\Database\_A.edb, and for the location of the logs, enter C:\<new\_logs\_path>.

6. Optional: On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

### **Recovery Options**

Choose from the following recovery options:

### No Recovery

This option skips any rollforward recovery after the restore operation. The database remains in a Rollforward pending state until you decide whether you want to run the rollforward recovery manually.

### Recover until end of backup

Restore the selected database to the state at the time the backup was created.

### Recover until end of available logs

This option restores the database and applies all available logs (including logs newer than the backup that might exist on the application server) to recover the database up to the latest possible time. This option is available only if you selected **Enable Log Backup** in the backup iob.

## Recover until specific point in time

When log backups are enabled, this option restores the database and applies logs from the log backup volume to recover the database up to an intermediate, user-specified point in time. Choose the date and time by selecting from the **By Time** options.

## **Application Options**

Set the application options:

### **Maximum Parallel Streams per Database**

Set the maximum data stream from the backup storage per database. This setting applies to each database in the job definition. Multiple databases can still be restored in parallel if the value of the option is set to 1. Multiple parallel streams might improve restore speed, but high-bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring an Exchange database to its original location by using its original database name.

#### **Advanced Options**

Set the advanced job definition options:

## Run cleanup immediately on job failure

Enable this option to automatically clean up allocated resources as part of a restore if the recovery fails.

- 7. Optional: On the **Apply scripts** page, select the **Pre-Script** or **Post-Script** to apply, or choose **Continue job/task on script error**. For more information about working with scripts, see <u>Configuring</u> scripts. Click **Next** to continue.
- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

The restore job is created, and you can check on its status in **Jobs and Operations** > **Running Jobs**.

### Restoring an Exchange database to an alternative instance

You can select a Microsoft Exchange database backup and restore it to an Exchange Server instance on an alternative host. You can restore the database in production mode or test mode to the alternative instance.

## Before you begin

Ensure that the following requirements are met:

- Enough disk space and allocated dedicated volumes are available for the copying of files.
- The file system structure on the source server is the same as the file system structure on the target server. This file system structure includes table spaces, online logs, and the local database directory.

#### **Procedure**

1. In the navigation pane, click **Manage Protection** > **Applications** > **Exchange** > **Create Restore Job** to open the "Snapshot restore" wizard.

### Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore
   Job > Exchange.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the plus icon next to the database that you want to use as the source of the restore operation. You can select more than one database from the list.

The selected sources are added to the restore list next to the database list. To remove an item from the list, click the minus icon next to the item.

- c) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Restore Type	Select the type of restore job:
	On-Demand: Snapshot Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-Demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring Creates a repeating point-in-time restore job that runs on a schedule.
Restore Location Type	Select a type of location from which to restore data:  Site  The site where snapshots were backed up. The site is defined on the System Configuration > Site pane.

Option	Description
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	<b>Demo</b> The demonstration site from which to restore snapshots.
	Primary  The primary site location from which to restore snapshots.
	Secondary  The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

- 4. On the **Set destination page**, choose **Restore to alternate instance**, select the target instance that you want to restore the database to and then click **Next**.
- 5. On the Restore method page, choose from the following options:
  - **Test**. In test mode, the agent creates a new database by using the data files directly from the vSnap repository. This restore type might be used for testing purposes.
  - **Production**. In production mode, the agent first restores the files from the vSnap volume back to primary storage and then creates the new database by using the restored files.
  - a) In the **New Database Name** field, enter a new database name.

b) (Production restore only) Expand the database name to see the source and destination path information. In the **Destination Path** field, enter the directory location of the Exchange database file on the alternative host, including the .edb name, and the logs location.



**Warning:** The destination directories that you enter in the **Destination Path** field must already exist on the alternative host. If not, then create the necessary directories on the alternative host before you complete the restore operation.

For example, for a database that is named Database\_A, enter C:\<new\_destination\_path>\Database\_A.edb, and for the location of the logs, enter c:\<new\_logs\_path>.

6. Optional: On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

### **Recovery Options**

Choose from the following recovery options:

## **No Recovery**

This option skips any rollforward recovery after the restore operation. The database remains in a Rollforward pending state until you decide whether you want to run the rollforward recovery manually.

## Recover until end of backup

Restore the selected database to the state at the time the backup was created.

### Recover until end of available logs

This option restores the database and applies all available logs (including logs newer than the backup that might exist on the application server) to recover the database up to the latest possible time. This option is available only if you selected **Enable Log Backup** in the backup job.

### Recover until specific point in time

When log backups are enabled, this option restores the database and applies logs from the log backup volume to recover the database up to an intermediate, user-specified point in time. Choose the date and time by selecting from the **By Time** options.

### **Application Options**

Set the application options:

### **Maximum Parallel Streams per Database**

Set the maximum data stream from the backup storage per database. This setting applies to each database in the job definition. Multiple databases can still be restored in parallel if the value of the option is set to 1. Multiple parallel streams might improve restore speed, but high-bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring an Exchange database to its original location by using its original database name.

### **Advanced Options**

Set the advanced job definition options:

### Run cleanup immediately on job failure

Enable this option to automatically clean up allocated resources as part of a restore if the recovery fails.

- 7. Optional: On the **Apply scripts** page, select the **Pre-Script** or **Post-Script** to apply, or choose **Continue job/task on script error**. For more information about working with scripts, see <u>Configuring scripts</u>. Click **Next** to continue.
- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

The restore job is created, and you can check on its status in **Jobs and Operations** > **Running Jobs**.

### Restoring individual mailbox items by using a granular restore operation

You can restore Microsoft Exchange individual mailbox items by using a granular restore operation and the IBM Spectrum Protect Plus Microsoft Management Console (MMC) GUI.

### Before you begin

You must have role-based access control (RBAC) permissions to complete individual mailbox restore operations. If RBAC permissions were not assigned, you might encounter configuration errors in the IBM Spectrum Protect Plus MMC GUI for each missing role.

### Tip:

If you encounter role-based configuration errors in the IBM Spectrum Protect Plus MMC GUI, you can set the required permissions manually to resolve the errors (see "Privileges" on page 151), or you can run the IBM Spectrum Protect Plus configuration wizard to automatically configure permissions (see step "14" on page 169).

### **About this task**

To start a granular restore operation, complete preparatory steps in the IBM Spectrum Protect Plus GUI, and then log in to the Exchange application server. Then, use the IBM Spectrum Protect Plus MMC GUI to restore user mailbox data from the recovery database that is created by the granular restore operation. A granular restore operation can be used to complete the following tasks:

- You can restore selected mailbox items to the original mailbox, another online mailbox on the same server, or to a Unicode .pst file.
- You can restore a public folder mailbox database, a public folder mailbox, or only a part of the mailbox, for example, a specific public folder.
- You can restore an archive mailbox or a part of the mailbox, for example, a specific folder.
- You can restore archive mailbox messages to a mailbox that is on the Exchange Server, to an archive mailbox, or to an Exchange Server . pst file.

### **Procedure**

1. In the navigation pane, click **Manage Protection** > **Applications** > **Exchange** > **Create Restore Job** to open the "Snapshot restore" wizard.

### Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore Job > Exchange.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the plus icon to the database that you want to use as the source of the restore operation.

**Tip:** You must select only one database for a granular restore operation. If you select multiple databases, the granular restore option will not be available on the **Restore method** page.

The selected source is added to the restore list next to the database list. To remove an item from the list, click the minus icon next to the item.

c) Click **Next** to continue.

3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description Description
Restore Type	Select the type of restore job:
	On-Demand: Snapshot  Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-Demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring  Creates a repeating point-in-time restore job that runs on a schedule.
Restore Location Type	Select a type of location from which to restore data:  Site
	The site where snapshots were backed up. The site is defined on the <b>System Configuration</b> > <b>Site</b> pane.
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive  The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	Demo The demonstration site from which to restore snapshots.
	The primary site location from which to restore snapshots.
	Secondary  The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.

Option	Description
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

- 4. On the Set destination page, select Restore to original instance and click Next.
- 5. On the **Restore method** page, click **Granular Restore**.
  - The recovery database name is displayed in the **New Database Name** field. The name consists of the existing database name with the suffix \_RDB.
- 6. Optional: In the **Job Options** page, **Recover until end of backup** and **Run cleanup immediately on job failure** are selected by default. Click **Next** to continue.
- 7. Optional: On the **Apply scripts** page, select the **Pre-Script** or **Post-Script** to apply, or choose **Continue job/task on script error**. For more information about working with scripts, see <u>Configuring</u> scripts. Click **Next** to continue.
- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.
  - The restore job is created, and you can check on its status in **Jobs and Operations** > **Running Jobs**.
- 10. In the navigation pane, click **Jobs and Operations** > **Active Resources** to view the recovery database and mount point details.
  - **Tip:** Click the icon to display an information message that describes the next steps for completing the granular restore task.
- 11. Connect to the Exchange application server instance by using Remote Desktop Connection (RDC) or Virtual Network Computing (VNC) if connecting remotely, or by logging on to the Exchange Server machine locally.
  - The granular restore operation automatically installs and starts the IBM Spectrum Protect Plus MMC GUI on the application server. If the MMC GUI fails to start, start it manually by using the path that is provided in the **Active Resources** information message.
- 12. In the IBM Spectrum Protect Plus MMC GUI, click the **Protect and Recover Data** node, and select **Exchange Server**.
- 13. On the **Recover** tab for the Exchange Server instance, click **View** > **Mailbox Restore Browser** to view the mailbox from the recovery database.
- 14. Optional: Run the IBM Spectrum Protect Plus configuration wizard:
  - a) In the navigation pane, click **Dashboard > Manage > Configuration > Wizards > IBM Spectrum Protect Plus Configuration**.
  - b) In the **Actions** pane, click **Start**.
    - The configuration wizard runs the requirements check.
  - c) When the requirements checks have run, click the Warnings link next to User Roles Check.
  - d) On the message dialog box, to add any missing roles, click Yes.
  - e) On the configuration wizard, click **Next**, and then click **Finish**.
- 15. In the **Mailbox Restore Browser > Source** tree, click the mailbox that contains the items you want to restore, which enables you to browse the individual folders and messages.
  - Choose from the following actions to select the folder or message to restore.

Table 19. Previewing and filtering mailbox items	
Task	Action
Preview mailbox items	a. Select a mailbox item, such as <b>Inbox</b> , to display its contents in the preview pane.
	b. Click an individual item in the preview pane, such as an email message, to view the message text and details.
	c. If an item contains an attachment, click the attachment icon to preview its contents.
Filter mailbox items	Use the filter options to narrow the list of folders and messages to restore:
	a. Click <b>Show Filter Options</b> and <b>Add Row</b> .
	b. Click the down arrow in the <b>Column Name</b> field and select an item to filter. You can filter by folder name, subject text, and other options.
	<b>Restriction:</b> You can filter public mailbox folders only by the <b>Folder Name</b> column.
	When you select <b>All Content</b> , the mailbox items are filtered by attachment name, sender, subject, and message body.
	c. In the <b>Operator</b> field, select an operator: Contains.
	d. In the <b>Value</b> field, specify a filter value.
	e. To specify additional filtering criteria, click <b>Add Row</b> .
	f. Click <b>Apply Filter</b> to filter the messages and folders.

- 16. When you have selected the mailbox item to restore, in the **Actions** pane, click the restore task that you want to run. Choose from the following options:
  - Restore Folder to Original Mailbox
  - Restore Messages to Original Mailbox
  - Save Mail Message Content

**Tip:** If you click **Save Mail Message Content**, a Windows Save File window is displayed. Specify the location and message name and click **Save**.

When you choose the restore option, the **Restore Progress** window opens and shows the progress of the restore operation, and the mailbox item is restored.

17. To restore a mailbox item to another mailbox or .pst file, complete the following steps.

**Note:** You can also restore a complete mailbox to another mailbox or .pst file.

Choose from the actions in the following table:

Table 20. Restoring a mailbox item to another r	nailbox or .pst file
Task	Action
Restore a mailbox item (or a mailbox) to a different mailbox	a. On the <b>Actions</b> pane, click <b>Open Exchange Mailbox</b> .
	b. Enter the alias of the mailbox to identify it as the restore destination.
	c. Drag the source mailbox item (or mailbox) to the destination mailbox on the results pane.
	<b>Restriction:</b> You cannot drag mail items or subfolders in the Recoverable Items folder to a destination mailbox.
Restore a mailbox item (or mailbox) to an Outlook personal folders (.pst) file	a. On the <b>Actions</b> pane, click <b>Open non- Unicode PST File</b> .
	b. When the <b>Open File</b> window opens, select an existing . pst file or create a . pst file.
	c. Drag the source mailbox item (or mailbox) to the destination . pst file on the results pane.
	<b>Restriction:</b> You can use the <b>Mailbox Restore Browser</b> view only with non-Unicode . pst files.
Restore a Public Folder	Select this action to restore a public folder to an existing online public folder mailbox.
	You can filter the mailbox and restore a specific public folder to an existing online public folder. In the <b>Folder to be restored</b> field, enter the name of the public folder that you want to restore.
	• To restore a subfolder in a parent folder, specify the full folder path in this format: parent_folder_name/sub_folder_name.
	<ul> <li>To restore all subfolders in a parent folder, use parent_folder_name/*.</li> </ul>
	• If the full folder path includes spaces, enclose the folder path in double quotation marks, and do not append a backslash character (\).
	You can also restore all or part of a public folder to a different public folder mailbox than the original mailbox. In the <b>Target public folder mailbox</b> field, specify the destination public folder mailbox that you want to restore to.

18. In the **Actions** pane, click **Close Exchange Mailbox** or **Close PST File** to close the destination mailbox or .pst file.

**Tip:** You can enable the Microsoft Management Console to gather diagnostic information to assist in problem determination related to restore operations. The process gathers configuration files, trace files, and overall diagnostics of the MMC GUI. For more information, see the following technote: <a href="mailto:Enabling diagnostic">Enabling diagnostic information in the IBM Spectrum Protect Plus MMC GUI(http://www.ibm.com/support/docview.wss?uid=ibm10882270)</a>.

19. When the restore operation for the individual items is finished, return to IBM Spectrum Protect Plus. In the **Jobs and Operation** > **Active Resources** pane, click **Actions** > **Cancel Granular Restore** to end the granular restore process.

# Restoring mailboxes by using a granular restore operation

You can restore Microsoft Exchange mailboxes by using a granular restore operation and the IBM Spectrum Protect Plus Microsoft Management Console (MMC) GUI.

#### Before you begin

You must have role-based access control (RBAC) permissions to complete individual mailbox restore operations. If RBAC permissions were not assigned, you might encounter configuration errors in the IBM Spectrum Protect Plus MMC GUI for each missing role.

## Tip:

If you encounter role-based configuration errors in the IBM Spectrum Protect Plus MMC GUI, you can set the required permissions manually to resolve the errors (see "Privileges" on page 151), or you can run the IBM Spectrum Protect Plus configuration wizard to automatically configure permissions (see step "14" on page 174).

#### **About this task**

To start a granular restore operation, complete preparatory steps in the IBM Spectrum Protect Plus GUI, and then log in to the Exchange application server. Then use the IBM Spectrum Protect Plus MMC GUI to restore user mailbox data from the recovery database that is created by the granular restore operation. A granular restore operation can be used to complete the following tasks:

- You can restore an entire mailbox or selected mailbox items to the original mailbox, another online mailbox on the same server, or to a Unicode .pst file.
- You can restore a public folder mailbox database, a public folder mailbox, or only a part of the mailbox, for example, a specific public folder.
- You can restore an archive mailbox or a part of the mailbox, for example, a specific folder.
- You can restore archive mailbox messages to a mailbox that is on the Exchange Server, to an archive mailbox, or to an Exchange Server . pst file.

#### **Procedure**

1. In the navigation pane, click **Manage Protection** > **Applications** > **Exchange** > **Create Restore Job** to open the "Snapshot restore" wizard.

## Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore Job > Exchange.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the plus icon ext to the database that you want to use as the source of the restore operation.

**Tip:** You must select only one database for a granular restore operation. If you select multiple databases, the granular restore option will not be available on the **Restore method** page.

The selected source is added to the restore list next to the database list. To remove an item from the list, click the minus icon next to the item.

- c) Click **Next** to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Restore Type	Select the type of restore job:
	On-Demand: Snapshot Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-Demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring Creates a repeating point-in-time restore job that runs on a schedule.
Restore Location Type	Select a type of location from which to restore data: Site
	The site where snapshots were backed up. The site is defined on the <b>System Configuration &gt; Site</b> pane.
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	<b>Demo</b> The demonstration site from which to restore snapshots.
	Primary  The primary site location from which to restore snapshots.
	Secondary  The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.

Option	Description
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

- 4. On the Set destination page, select Restore to original instance and click Next.
- 5. On the **Restore method** page, click **Granular Restore**.

The recovery database name is displayed in the **New Database Name** field. The name consists of the existing database name with the suffix \_RDB.

- 6. Optional: In the **Job Options** page, **Recover until end of backup** and **Run cleanup immediately on job failure** are selected by default. Click **Next** to continue.
- 7. Optional: On the **Apply scripts** page, select the **Pre-Script** or **Post-Script** to apply, or choose **Continue job/task on script error**. For more information about working with scripts, see <u>Configuring</u> scripts. Click **Next** to continue.
- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

The restore job is created, and you can check on its status in **Jobs and Operations** > **Running Jobs**.

10. In the navigation pane, click **Jobs and Operations** > **Active Resources** to view the recovery database and mount point details.

**Tip:** Click the icon to display an information message that describes the next steps for completing the granular restore task.

11. Connect to the Exchange application server instance by using Remote Desktop Connection (RDC) or Virtual Network Computing (VNC) if connecting remotely, or by logging on to the Exchange Server machine locally.

The granular restore operation automatically installs and starts the IBM Spectrum Protect Plus MMC GUI on the application server. If the MMC GUI fails to start, start it manually by using the path that is provided in the **Active Resources** information message.

- 12. In the IBM Spectrum Protect Plus MMC GUI, click the **Protect and Recover Data** node, and select **Exchange Server**.
- 13. On the **Recover** tab for the Exchange Server instance, select **View > Mailbox Restore**.

A list of user mailboxes from all databases that are included in the backup is displayed.

- 14. Optional: Run the IBM Spectrum Protect Plus configuration wizard:
  - a) In the navigation pane, click **Dashboard > Manage > Configuration > Wizards > IBM Spectrum Protect Plus Configuration**.
  - b) In the Actions pane, click Start.

The configuration wizard runs the requirements check.

- c) When the requirements checks have run, click the Warnings link next to User Roles Check.
- d) On the message dialog box, to add any missing roles, click Yes.
- e) On the configuration wizard, click **Next**, and then click **Finish**.

15. Select one or more mailboxes from the recovery database to restore. Mailboxes are listed by Mailbox Name, Alias, Server, Database, and Mailbox Type.

You can restore only user mailboxes that are located in the recovery database.

**Tip:** Mailboxes from other databases are shown in this view for informational purposes only. If the mailbox that you want to restore is not in the recovery database, use this view to determine which Exchange database the user mailbox was assigned to. You can then run the granular restore task again for that database.

16. To complete the restore operation, in the **Actions** pane, click one of the following restore options.

Table 21. Restore options	
Option	Action
Restore Mail to Original Location	Restore mail items to their location at the time of the backup operation.
Restore Mail to Alternate Location	Restore the mail items to a different mailbox.
	On the Alternate Mailbox Options window, enter the Mailbox alias name.
	Tip: If deleted mail items or tasks are flagged in the Recoverable Items folder of a mailbox, the items are restored with the flag attribute to the Flagged Items and Tasks view in the target mailbox.
Restore Mail to non-Unicode PST file Restriction:	Restore mail items to a non-Unicode personal folders (.pst) file.
<ul> <li>This option is available only for Exchange Server 2013.</li> <li>Each folder can contain a maximum of 16,383 mail items.</li> </ul>	When you restore mail items to a .pst file with one selected mailbox, you are prompted for a file name. When you restore mail items to a .pst file with more than one selected mailbox, you are prompted for a directory location. Each mailbox is restored to a separate .pst file that reflects the name of the mailbox at the specified directory.
	If the .pst file exists, the file is used. Otherwise, the file is created.
Restore Mail to Unicode PST file	Restore mail items to a Unicode .pst file.
	When you restore mail items to a .pst file with one selected mailbox, you are prompted for a file name. When you restore mail items to a .pst file with more than one selected mailbox, you are prompted for a directory location.
	Tip:
	You can enter a standard path name (for example, c:\PST\mailbox.pst) or a UNC path (for example, \\server\c\$\PST\mailbox.pst). When you enter a standard path, the path is converted to a UNC path. If the UNC is a non-default UNC path, enter the UNC path directly.
	Each mailbox is restored to a separate .pst file that reflects the name of the mailbox at the specified directory. If the .pst file exists, the file is used. Otherwise, the file is created.

Table 21. Restore options (continued)		
Option	Action	
Restore Public Folder Mailbox	Restore a public folder mailbox to an online public folder mailbox.	
	In the <b>Folder to be restored</b> field, enter the name of the public folder that you want to restore:	
	• To restore a subfolder in a parent folder, specify the full folder path in this format: parent_folder_name/sub_folder_name.	
	<ul> <li>To restore all subfolders in a parent folder, use parent_folder_name/*.</li> </ul>	
	• If the full folder path includes spaces, enclose the folder path in double quotation marks, and do not append a backslash character (\).	
	You can also restore all or part of a public folder mailbox to a different public folder mailbox than the original mailbox. In the <b>Target public folder mailbox</b> field, specify the destination public folder mailbox.	
Restore Mail to Archive Mailbox	This action applies to a primary mailbox or an archive mailbox. Select this action to restore all or part of either type of mailbox to the original archive mailbox or to an alternative archive mailbox.	
	You can filter the archive mailbox and restore a specific mailbox folder. In the <b>Folder to be restored</b> field, enter the name of the folder in the archive mailbox that you want to restore.	
	• To restore a subfolder in a parent folder, specify the full folder path in this format: parent_folder_name/sub_folder_name.	
	<ul> <li>To restore all subfolders in a parent folder, use parent_folder_name/*.</li> </ul>	
	• If the full folder path includes spaces, enclose the folder path in double quotation marks, and do not append a backslash character (\).	
	In the <b>Target archive mailbox</b> field, specify the archive mailbox destination.	
Exclude recoverable mail items while restoring the mailbox	Apply this action if you are restoring an online, public folder, or archive mailbox to an original mailbox, alternative mailbox, or to a Unicode . pst file.	
	Specify a value of <b>Yes</b> to exclude the mail items in the Recoverable Items folder in mailbox restore operations. <b>No</b> is the default value.	

**Tip:** You can enable the Microsoft Management Console to gather diagnostic information to assist in problem determination related to restore operations. The process gathers configuration files, trace files, and overall diagnostics of the MMC GUI. For more information, see the following technote: Enabling diagnostic information in the IBM Spectrum Protect Plus MMC GUI(http://www.ibm.com/support/docview.wss?uid=ibm10882270).

17. When the mailbox restore operation is finished, return to IBM Spectrum Protect Plus. In the **Jobs and Operation** > **Active Resources** pane, click **Actions** > **Cancel Granular Restore** to end the granular restore process.

# **Restoring Database Availability Group backups**

With IBM Spectrum Protect Plus, you can restore an Exchange Server Database Availability Group (DAG) backup to the original instance or to an alternative instance.

#### About this task

In a DAG environment, you must restore a database to an active database copy. If you had selected a passive database copy as the preferred target of backup operations, IBM Spectrum Protect Plus attempts to restore the database to this passive copy by default. The restore operation fails. In this situation, you can choose to restore the database to an alternative instance, and then select the active database copy.

#### **Procedure**

To define an Exchange restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Applications** > **Exchange** > **Create Restore Job** to open the "Snapshot restore" wizard.

## Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore
   Job > Exchange.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. In the **Source select** page, complete the following steps:
  - a) Click the View menu and select Database Availability Groups.
  - b) In the **Availability Groups** list, click an Exchange instance to see the list of restore points for that instance and select the backup versions that you want to restore. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - c) Click the add to restore list icon next to the database that you want to use as the source of the restore operation. You can select more than one database from the list.

The selected sources are added to the restore list next to the database list. To remove an item from the list source, click the icon next to the item.

- d) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Restore Type	Select the type of restore job:
	On-Demand: Snapshot  Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-Demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring Creates a repeating point-in-time restore job that runs on a schedule.

Option	Description
Restore Location Type	Select a type of location from which to restore data:  Site  The site where snapshots were backed up. The site is defined on the System
	Configuration > Site pane.
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	<b>Demo</b> The demonstration site from which to restore snapshots.
	Primary  The primary site location from which to restore snapshots.
	Secondary  The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

4. In the **Set destination** page, specify where you want to restore the database and click **Next**.

# Restore to original instance

Select this option to restore the database to the original server.

# Restore to alternate instance

Select this option to restore the database to a local destination that is different from the original server, then select the alternative location from the list of available servers.



**Attention:** When you choose the destination, you must select an active node as the destination; otherwise, the restore operation fails.

- 5. In the **Restore method** page, choose from the following options:
  - **Test**. Choose this option to restore the data from the vSnap repository directly. This restore type might be used for testing purposes.
  - **Production**. Choose this option to restore the full database with a full-copy data restore operation. This restore operation is for permanent use of the restored database.

Click **Next** to continue.

6. Optional: On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

# **Recovery Options**

Choose from the following recovery options:

#### No Recovery

This option skips any rollforward recovery after the restore operation. The database remains in a Rollforward pending state until you decide whether you want to run the rollforward recovery manually.

# Recover until end of backup

Restore the selected database to the state at the time the backup was created.

# Recover until end of available logs

This option restores the database and applies all available logs (including logs newer than the backup that might exist on the application server) to recover the database up to the latest possible time. This option is available only if you selected **Enable Log Backup** in the backup job.

# Recover until specific point in time

When log backups are enabled, this option restores the database and applies logs from the log backup volume to recover the database up to an intermediate, user-specified point in time. Choose the date and time by selecting from the **By Time** options.

## **Application Options**

Set the application options:

# **Maximum Parallel Streams per Database**

Set the maximum data stream from the backup storage per database. This setting applies to each database in the job definition. Multiple databases can still be restored in parallel if the value of the option is set to 1. Multiple parallel streams might improve restore speed, but high-bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring an Exchange database to its original location by using its original database name.

# **Advanced Options**

Set the advanced job definition options:

# Run cleanup immediately on job failure

Enable this option to automatically clean up allocated resources as part of a restore if the recovery fails.

- 7. Optional: On the **Apply scripts** page, select the **Pre-Script** or **Post-Script** to apply, or choose **Continue job/task on script error**. For more information about working with scripts, see <u>Configuring</u> scripts. Click **Next** to continue.
- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

The restore job is created, and you can check on its status in **Jobs and Operations** > **Running Jobs**.

# Accessing Exchange database files with instant access mode

You can access the Microsoft Exchange database files by using the instant access restore type and mount the database files from the vSnap volume to an application server.

#### **About this task**

In instant access mode, no further action is taken after IBM Spectrum Protect Plus mounts the share. Use the data for custom recovery of data from the files in the vSnap volume.

#### **Procedure**

1. In the navigation pane, click **Manage Protection** > **Applications** > **Exchange** > **Create Restore Job** to open the "Snapshot restore" wizard.

## Tips:

- You can also open the "Snapshot restore" wizard by clicking **Jobs and Operations** > **Create Restore Job** > **Exchange**.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the plus icon ext to the database that you want to use as the source of the restore operation. You can select more than one database from the list.
    - The selected sources are added to the restore list next to the database list. To remove an item from the list, click the minus icon next to the item.
  - c) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Restore Type	Select the type of restore job:
	On-Demand: Snapshot  Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-Demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring Creates a repeating point-in-time restore job that runs on a schedule.
Restore Location	Select a type of location from which to restore data:
Туре	Site  The site where snapshots were backed up. The site is defined on the System Configuration > Site pane.
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.

Option	Description
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.  Cloud Archive
	The cloud server on which snapshots were archived. The cloud server is defined on the <b>System Configuration</b> > <b>Backup Storage</b> > <b>Cloud</b> pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	<b>Demo</b> The demonstration site from which to restore snapshots.
	Primary  The primary site location from which to restore snapshots.
	Secondary The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

4. On the **Set destination** page, specify where you want to mount the database files and click **Next**.

Option	Description
Restore to original location	Select this option to mount the database files to the original server.
Restore to alternate location	Select this option to mount the database files to a local destination that is different from the original server, and then select the alternative location from the list of available servers.

- 5. On the **Restore Method** page, choose **Instant Access**, and then click **Next**.
- 6. Optional: On the **Job options** page, configure additional options if necessary and click **Next** to continue.
- 7. Optional: On the **Apply scripts** page, select the **Pre-Script** or **Post-Script** to apply, or choose **Continue job/task on script error**. For more information about working with scripts, see <u>Configuring</u> scripts. Click **Next** to continue.

- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click Next.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

  The restore job is created, and you can check on its status in **Jobs and Operations** > **Running Jobs**.
- 10. You can now access the Exchange database files on the application server mount point, and carry out any Exchange related or custom actions you want to do.
  - **Note:** The Exchange database files on the mount point are read/write. However, updating them does not modify the original backup.
- 11. When you are finished with the instant access restore operation, go to the **Active Resources** pane, click **Actions** > **Cancel Restore** to remove the mounted database and end the restore process.

# **Mongo DB**

After you successfully add MongoDB instances to IBM Spectrum Protect Plus, you can start to protect the data in your MongoDB databases. Create service level agreement (SLA) policies to back up and maintain MongoDB data.

Ensure that your MongoDB environment meets the system requirements. For more information, see "MongoDB requirements" on page 32.

# **Prerequisites for MongoDB**

All system requirements and prerequisites for the IBM Spectrum Protect Plus MongoDB application server must be met before you start protecting MongoDB data with IBM Spectrum Protect Plus.

For MongoDB system requirements, see MongoDB system requirements.

To meet the prerequisites for MongoDB, complete the following checks and actions.

- 1. Ensure you have met the space prerequisites, as described in <u>Space requirements for MongoDB</u> protection.
- 2. Set the file size limit for the MongoDB instance user with the command **ulimit** -f to unlimited. Alternatively, set the value to sufficiently high to allow the copying of the largest database files in your backup and restore jobs. If you change the **ulimit** setting, restart the MongoDB instance to finalize the configuration.
- 3. If you are running MongoDB in an AIX or Linux environment, ensure that the installed sudo version is at a supported level.
  - For more information about the version level, see "MongoDB requirements" on page 32. For information about setting sudo privileges, see "Setting sudo privileges" on page 184.
- 4. If your MongoDB databases are protected by authentication, you must set up role-based access control. For more information, see "Roles for MongoDB" on page 183.
- 5. Each MongoDB instance to be protected must be registered on IBM Spectrum Protect Plus. After the instances are registered, IBM Spectrum Protect Plus runs an inventory to detect MongoDB resources. Ensure that all instances that you want to protect are detected and listed correctly.
- 6. Ensure that the SSH service is running on port 22 on the server, and that firewalls are configured to allow IBM Spectrum Protect Plus to connect to the server with SSH. The SFTP subsystem for SSH must be enabled.
- 7. Ensure that you do not configure nested mount points.

#### Restrictions

The following restrictions apply to the MongoDB application server:

- MongoDB sharded cluster configurations are detected when you run an inventory, but these resources are not eligible for backup or restore operations.
- Unicode characters in MongoDB file path names cannot be handled by IBM Spectrum Protect Plus. All names must be in ASCII.

#### Virtualization

Protect your MongoDB environment with IBM Spectrum Protect Plus when it is running on one of the following guest operating systems:

- · Red Hat Enterprise Linux
- SUSE Linux Enterprise Server Kernel-based Virtual Machine (KVM)

# **Roles for MongoDB**

You must define role-based access control (RBAC) roles for the MongoDB agent users if authentication is enabled on the MongoDB database. When the roles are set up, users can protect and monitor MongoDB resources with IBM Spectrum Protect Plus in accordance with the users' defined roles.

## Role-based access control for MongoDB

For each MongoDB user, specify access roles by using a command similar to the following example:

```
use admin
db.grantRolesToUser("<username>",
[ { role: "hostManager", db: "admin" },
{ role: "clusterManager", db: "admin" } ] )
```

The following roles are available:

#### hostManager

This role provides access to the **fsyncLock** command. This access is required for application-consistent backups of MongoDB databases where journaling is not enabled. This role also provides access to the shutdown command, which is used during a restore operation to shut down the MongoDB server instance that the restore is directed to.

#### clusterMonitor

This role provides access to commands for monitoring and reading the state of the MongoDB database. The following commands are available to users with this role:

- getCmdLineOpts
- serverVersion
- replSetGetConfig
- replSetGetStatus
- isMaster
- · listShards

#### clusterManager

This role is only required only for running test restore operations of replica sets. Users who run the **replSetReconfig** command can create the restored instance of a single node replica set. This role enables read and write access during test restore operations of replica sets. Without this access, the node in the replica set would remain in the REMOVED state without read and write access. In addition, this role provides access to commands for reading the state of the MongoDB database. The following commands are available for this role:

- replSetReconfig
- getCmdLineOpts
- serverVersion

- replSetGetConfig
- replSetGetStatus
- isMaster
- · listShards

## **Space prerequisites for MongoDB protection**

Before you start backing up MongoDB data, ensure that you have enough free space on the target and source hosts, and in the vSnap repository. Extra space is required to store temporary Logical Volume Manager (LVM) backups of logical volumes where the MongoDB data is located. These temporary backups, that are known as LVM snapshots, are created automatically by the MongoDB agent.

## LVM snapshots

LVM snapshots are point-in-time copies of LVM logical volumes. After the file copy operation finishes, earlier LVM snapshots are removed by the IBM Spectrum Protect Plus MongoDB agent in a cleanup operation.

For each LVM snapshot logical volume, you must allocate at least 10 percent free space in the volume group. If there is enough free space in the volume group, the IBM Spectrum Protect Plus MongoDB agent reserves up to 25 percent of the source logical volume size for the snapshot logical volume.

#### Linux LVM2

When you run a MongoDB backup operation, MongoDB requests a snapshot. This snapshot is created on a Logical Volume Management (LVM) system for each logical volume with data or logs for the selected database. On Linux systems, logical volumes are managed by LVM2.

A software-based LVM2 snapshot is taken as a new logical volume on the same volume group. The snapshot volumes are temporarily mounted on the same machine that runs the MongoDB instance so that they can be transferred to the vSnap repository.

On Linux, the LVM2 volume manager stores the snapshot of a logical volume within the same volume group. There must be enough space available to store the logical volume. The logical volume grows in size as the data changes on the source volume for the lifetime of the snapshot.

## **Setting sudo privileges**

To use IBM Spectrum Protect Plus to protect your data, you must install the required version of the sudo program.

#### **About this task**

Set up a dedicated IBM Spectrum Protect Plus agent user with the required superuser privileges for sudo. This configuration enables agent users to run commands without a password.

#### **Procedure**

1. Create an agent user by issuing the following command:

```
useradd -m agent
```

where agent specifies the name of the IBM Spectrum Protect Plus agent user.

2. Set a password for the new user by issuing the following command:

```
passwd mongodb_agent
```

3. To enable superuser privileges for the agent user, set the !requiretty setting. At the end of the sudo configuration file, add the following lines:

```
Defaults:agent !requiretty
agent ALL=(ALL) NOPASSWD:ALL
```

Alternatively, if your sudoers file is configured to import configurations from another directory, for example /etc/sudoers.d, you can add the lines in the appropriate file in that directory.

# Adding a MongoDB application server

To start protecting MongoDB resources, you must add the server that hosts your MongoDB instances, and set credentials for the instances. Repeat the procedure to add all the servers that host MongoDB resources.

#### **About this task**

To add a MongoDB application server to IBM Spectrum Protect Plus, you must have the host address of the machine.

#### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > MongoDB.
- In the MongoDB window, click Manage Application Servers, and click Add Application Server to add the host machine.



- 3. In the **Application Properties** form, enter the host address.
- 4. Choose to register the host with a user or an SSH key.

If you select **User**, you can choose to enter a new user and password, or an existing user. If you select **SSH Key**, select the SSH key from the menu.

**Restriction:** Any user that is specified must have sudo privileges set up.




Figure 25. Adding a MongoDB agent

5. Click **Get Instances** to detect and list the MongoDB instances that are available on the host server that you are adding.

Each MongoDB instance is listed with its connection host address, status, and an indication of whether it is configured.



**Attention:** If you register more than one application server for one replica set, the instance name that is displayed might change after each inventory, backup, or restore operation. The host name of the most recently added application server that belongs to the replica set is used as part of the instance name. An inventory operation is run as part of backup and restore operations.

6. If you are using access control, configure an instance by setting credentials. Click **Set Credential**, and set the user ID, and password. Alternatively, you can select to use an existing user profile.

For more information about access control, see Chapter 13, "Managing user access," on page 275.

When you set credentials, you assign MongoDB user roles for the backup and restore operations with access to role-protected MongoDB servers by using Salted Challenge Response Authentication Mechanism (SCRAM), or Challenge and response authentication. The MongoDB user that is assigned for the role-protected MongoDB server requires one of the following access levels to protect resources:

- Host Manager: manages the database as the administrator. This role is required for taking and managing snapshots.
- Cluster Administrator: retrieves configuration information and runs test mode restore operations of MongoDB replica sets. This role is required to reconfigure test mode restore operations of MongoDB replica sets for data queries.
- Cluster Monitor: monitors the protection of MongoDB resources, and retrieves configuration information.
- 7. Optional: Set the option **Maximum concurrent databases** by entering a number in the field.
- 8. Save the form, and repeat the steps to add other MongoDB application servers to IBM Spectrum Protect Plus.

## What to do next

After you add MongoDB application servers to IBM Spectrum Protect Plus, an inventory is automatically run on each application server to detect the relevant databases in those instances.

To verify that the databases are added, review the job log. Go to **Jobs and Operations**. Click the **Running Jobs** tab, and look for the latest Application Server Inventory log entry.

Completed jobs are shown on the **Job History** tab. You can use the **Sort By** list to sort jobs based on start time, type, status, job name, or duration. Use the **Search by name** field to search for jobs by name. You can use asterisks as a wildcard in the name.

Databases must be detected to ensure that they can be protected. For instructions about running a manual inventory, see Detecting MongoDB resources.

## **Detecting MongoDB resources**

After you add your MongoDB application servers to IBM Spectrum Protect Plus, an inventory is run automatically to detect all MongoDB instances and databases. You can run a manual inventory on any application server to detect, list, and store all MongoDB databases for the selected host.

# Before you begin


Ensure that you added your MongoDB application servers to IBM Spectrum Protect Plus. For instructions, see Adding a MongoDB application server.

## **Procedure**

1. In the navigation pane, expand Manage Protection > Applications > MongoDB.

**Tip:** To add more MongoDB instances to the **Instances** pane, follow the instructions in <u>Adding a MongoDB application server</u>.

2. Click Run Inventory.



When the inventory is running, the button changes to **Inventory In Progress**. You can run an inventory on any available application servers, but you can run only one inventory process at a time.

To monitor the inventory job, go to **Jobs and Operations**. Click the **Running Jobs** tab, and look for the latest Application Server Inventory log entry.

Completed jobs are shown on the **Job History** tab. You can use the **Sort By** list to sort jobs based on start time, type, status, job name, or duration. Use the **Search by name** field to search for jobs by name. You can use asterisks as wildcard characters in the name.

3. Click an instance to open a view that shows the databases that are detected for that instance. If any databases are missing from the **Instances** list, check your MongoDB application server and rerun the inventory. In some cases, certain databases are marked as ineligible for backup; hover over the database to reveal the reason why.

**Tip:** To return to the list of instances, click the **Instances** link in the **Backup MongoDB** pane.



**Attention:** If you register more than one application server for one replica set, the instance name that is displayed might change after each inventory, backup, or restore operation. The host name of the most recently inventoried application server that belongs to the replica set is used as part of the instance name. An inventory operation is run as part of backup and restore operations.

#### What to do next

To start protecting MongoDB databases that are cataloged in the selected instance, apply a service level agreement (SLA) policy to the instance. For instructions about setting an SLA policy, see <u>Defining an SLA policy</u>.

## **Testing the MongoDB connection**


After you add a MongoDB application server, you can test the connection. The test verifies communication between IBM Spectrum Protect Plus and the MongoDB server. It also checks that the correct sudo permissions area available for the user who is running the test.

#### **Procedure**

- 1. In the navigation pane, click Manage Protection > Applications > MongoDB.
- 2. In the **MongoDB** window, click **Manage Application Servers**, and select the host address that you want to test.

A list of the MongoDB application servers that are available is shown.

3. Click **Actions** and choose **Test** to start the verification tests for physical and remote system connections and settings.



The test report displays a list that includes tests for the physical host network configuration, and tests for the remote server installation on the host.

4. Click **OK** to close the test report. If issues are reported, fix the issues and rerun the test to verify the fixes.

# **Backing up MongoDB data**

Define regular MongoDB backup jobs with options to run and create backup copies to protect your data. To regularly back up your data, define a backup job that includes a service level agreement (SLA) policy.

# Before you begin

During the initial backup operation, IBM Spectrum Protect Plus creates a new vSnap volume and NFS share. During incremental backups, the previously created volume is reused. The IBM Spectrum Protect Plus MongoDB agent mounts the share on the MongoDB server where the backup is completed.

Review the following prerequisites before you create a backup job definition:

- Add the application servers that you want to back up. For the procedure, see <u>Adding a MongoDB</u> application server.
- Configure an SLA Policy. For the procedure, see Defining a Service Level Agreement backup job.
- Before an IBM Spectrum Protect Plus user can set up backup and restore operations, roles and resource groups must be assigned to the user. Grant users access to resources, and backup and restore operations, in the **Accounts** pane. For more information, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275 and "Roles for MongoDB" on page 183.

**Restriction:** Do not run inventory jobs at the same time that backup jobs are scheduled.

#### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > MongoDB.
- 2. Select the check box for the instance that you want to back up.
  - Under each MongoDB instance, data to be backed up is listed as **ALL**. Each instance in the Instances pane is listed by instance name, version, and the applied SLA policy.
- 3. Click **Select Options** to specify the number of parallel streams for the backup operation, and then click **Save**. By selecting an appropriate number of parallel streams, you can minimize the time that is required for the backup job.
  - The saved options are used for all backup jobs for this instance as selected.
- 4. To run the backup job with these options, click the instance name, select the **ALL** database representation, and click **Run**.
  - The backup job begins, and you can view the details in **Jobs and Operation > Running Jobs**.
  - **Tip:** The **Run** button is only enabled if an SLA policy is applied to the **ALL** representation of the databases.
- 5. Select the instance again, and click **Select an SLA Policy** to choose an SLA policy.
- 6. Save the SLA selection.

To define a new SLA or to edit an existing policy with custom retention and frequency rates, select **Manage Protection** > **Policy Overview**. In the **SLA Policies** pane, click **Add SLA Policy**, and define policy preferences.

#### What to do next

After the SLA policy is saved, you can run the policy at any time by clicking **Actions** beside the policy name and selecting **Start**. The status in the log changes to show that the backup job is in the Running state.

To cancel a job that is running, click **Actions** beside the policy name and select **Cancel**. A message asks whether you want to keep the data that is already backed up. Choose **Yes** to keep the backed up data, or **No** to discard the backup.

# Defining a regular service level agreement job

After your MongoDB instances are listed, select and apply an SLA policy to start protecting your data.

#### **Procedure**

- 1. In the navigation pane, expand Manage Protection > Applications > MongoDB.
- 2. Select the MongoDB instance to back up all the data in that instance.




Figure 26. MongoDB Backup pane showing instances

- 3. Click **Select an SLA policy** and choose an SLA policy. Save your choice.
  - Predefined choices are Gold, Silver, and Bronze, each with different frequencies and retention rates. You can also create a custom SLA policy by navigating to **Policy Overview** > **Add SLA Policy**.
- 4. Optional: To enable multiple backup streams to reduce the time that is taken to back up large databases, click **Select Options** and enter a number of parallel streams. Save your changes.




Figure 27. Backup options and SLA Policy Status

- 5. Configure the SLA policy by clicking the icon in the **Policy Options** column of the **SLA Policy Status** table.
  - For more information about SLA configuration options, see <u>"Setting SLA configuration options for your backup"</u> on page 191.
- 6. To run the policy outside of the scheduled job, select the instance. Click the **Actions** button and select **Start**. The status changes to **Running** for your chosen SLA and you can follow the progress of the job in the log shown.

## What to do next

After the SLA policy is saved, you can run the policy at any time by clicking **Actions** beside the policy name and selecting **Start**. The status in the log changes to show that the backup job is in the Running state.

To cancel a job that is running, click **Actions** beside the policy name and select **Cancel**. A message asks whether you want to keep the data that is already backed up. Choose **Yes** to keep the backed up data, or **No** to discard the backup.

## **Setting SLA configuration options for your backup**

After you set up a service level agreement (SLA) policy for your backup job, you can choose to configure extra options for that job. Additional SLA options include running scripts, and forcing a full base backup.

#### **Procedure**

In the Policy Options column of the SLA Policy Status table for the job that you are configuring, click the clipboard icon to specify additional configuration options.
 If the job is already configured, click on the icon to edit the configuration.

Configure Options		×
Pre-Script Post-Script Continue job/task on script	error	
Exclude Resources	e.g. dbname (match) dbname* (wildcard)	
Force full backup of resources.	e.g. dbname (match) ";" separated	
Forcing a full backup of a re	source, runs a new full base backup of that resource.	
		Save

Figure 28. Specifying additional SLA configuration options

- 2. Click **Pre-Script** and define the prescript configuration by choosing one of the following options:
  - Click **Use Script Server** and select an uploaded script from the menu.
  - Do not click **Use Script Server**. Select an application server from the list to run the script at that location.
- 3. Click **Post-Script** and define the PostScript configuration by choosing one of the following options:
  - Click **Use Script Server** and select an uploaded script from the menu.
  - Do not click **Use Script Server**. Select an application server from the list to run the script at that location.

Scripts and script servers are configured on the **System Configuration** > **Script** page. For more information about working with scripts, see **Configuring scripts**.

4. To continue running the job when the script that is associated with the job fails, select **Continue job/** task on script error.

If this option is selected, the backup or restore operation is reattempted after an initial fail, and the script task status is reported as COMPLETED when the script completes processing with a nonzero return code. If this option is not selected, the backup or restore is not reattempted and the script task status is reported as FAILED.

- 5. Skip **Exclude Resources** for MongoDB SLA options, as you cannot specify resources to exclude. Instances are backed up rather than individual databases.
- 6. To create a full, new backup of a MongoDB instance, select **Force full backup of resources**.

  A full new backup of that resource is created to replace the existing backup of that resource for one occurrence only. After that the resource is backed up incrementally as before.

# **Restoring MongoDB data**

To restore data, define a job that restores data to the latest backup or select an earlier backup copy. Choose to restore data to the original instance or to an alternative instance on a different machine, creating a cloned copy. Define and save the restore job to run as an ad hoc operation, or to run regularly as a scheduled job.

# Before you begin

Before you create a restore job for MongoDB, ensure that the following requirements are met:

- At least one MongoDB backup job is set up and running successfully. For instructions about setting up a backup job, see "Backing up MongoDB data" on page 189.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is setting up the restore job. For instructions about assigning roles, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275, and "Roles for MongoDB" on page 183.
- Enough disk space is allocated at the target server for the restore operation.
- Dedicated volumes are allocated for file copying.
- The same directory structure and layout are available on both the target and source servers.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

For restore operations to alternative instances, MongoDB must be at the same version level on the target and host machines.

For more information about space requirements, see <u>Space prerequisites for MongoDB protection</u>. For more information about prerequisites and setup, see <u>Prerequisites for MongoDB</u>.

#### **Procedure**

To define a MongoDB restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Applications** > **MongoDB** > **Create Restore Job** to open the Snapshot restore wizard.

#### Tips:

- You can also start the Snapshot restore wizard by clicking Jobs and Operations > Create Restore
  Job > MongoDB.
- For a running summary of your selections in the Snapshot restore wizard, move the cursor to the



- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the add to restore list icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.
    - The selected sources are added to the restore list next to the database list. To remove an item from the list source, click the remove from restore list icon next to the item.
  - c) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Type of Restore	Select the type of restore job to run.
	On-Demand: Snapshot Performs a one-time restore operation from a snapshot backup.
	On-Demand: Point in Time Performs a one-time restore operation from a specific point-in-time backup.
	Recurring Performs scheduled restore operations of data from the latest restore points.
Restore	Select a type of location to restore from:
Location Type	Site
lype	Restores data from a site that is associated with the backup storage server.
	Cloud Offload  Restores data that is stored on cloud storage.
	Repository Offload
	Restores data that is stored on the repository server.
	Cloud Archive Restores data that is archived on cloud storage.
	Repository Archive
	Restores data that is archived on the repository server.
Select a location	If you are restoring data from a site, select one of the following restore locations:
location	<b>Demo</b> Restores data from the demonstration vSnap server that is set up for test purposes.
	<b>Primary</b> Restores data from the vSnap server that is the primary backup destination.
	Secondary Restores data from the vSnap server that is the secondary backup destination.
	If you are restoring data from a cloud or repository server, you do not have to make a selection because the location is already selected.
Date selector	For on-demand restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand restore operations, select a snapshot from the list of available snapshots in the selected date range.
Use alternate vSnap server for the restore job	Select this box to specify an alternative vSnap server when you are restoring a specific restore point from a cloud resource or repository server, and then select a server from the <b>Select alternate vSnap</b> menu.
	When you are restoring data from a restore point that was offloaded to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway for the restore operation.

4. On the **Set destination** page, select **Restore to original instance** to restore to the original server, or **Restore to alternate instance** to restore to a different location that you can select from the locations listed.

For more information about restoring data to the original instance, see <u>Restoring to the original instance</u>. For more information about restoring your data to an alternative instance, see <u>Restoring to an alternate</u> instance.

- 5. On the **Restore method** page, choose the type of restore operation, and click **Next** to continue.
  - **Test**: In this mode, the agent creates a database by using the data files directly from the vSnap repository. This option is available only when you are restoring data to an alternative instance. Members of replica sets will not be reconfigured after the MongoDB server is started. The server is started as a single-node replica set.
  - **Production**: In this mode, the MongoDB application server first copies the files from the vSnap repository to the target host. The copied data is then used to start the database. MongoDB instances that are members of a replica set are not started during a production restore operation. This action prevents data from being overwritten when connecting to the replica set.
  - **Instant Access**: In this mode, no further action is taken after IBM Spectrum Protect Plus mounts the share. Use the data for custom recovery from the files in the vSnap repository.

For test mode or production mode, you can optionally enter a new name for the restored database.

For production mode, you can also specify a new folder for the restored database by expanding the database and entering a new folder name.

6. Optional: On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

In the **Recovery Options** section, the **Recover until end of backup** for MongoDB is selected by default. This option recovers the selected data to the state it was in at the time the backup was created. The recovery operation makes use of the log files that are included in the MongoDB backup.

# **Application Options**

Set the application options:

# Overwrite existing database

Enable this option to allow the restore job to overwrite the selected database. If this option is not selected, the restore job fails when data with the same name is found during the restore process.



**Attention:** Ensure that no other data shares the same local database directory as the original data or the data will be overwritten.

## **Maximum Parallel Streams per Database**

Set the maximum number of parallel data streams from the backup storage per database. This setting applies to each database in the job definition. Multiple databases can still be restored in parallel if the value of the option is set to 1. Multiple parallel streams might speed up restore operations, but high bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring a MongoDB database to its original location by using its original database name.

## **Advanced Options**

Set the advanced job definition options:

#### Run cleanup immediately on job failure

This option is selected by default to automatically clean up allocated resources as part of a restore operation if recovery fails.

#### Allow session overwrite

Select this option to replace existing databases with the same name during a restore operation. During an instant disk restore operation, the existing database is shut down and overwritten, and then the recovered database is restarted. If this option is not selected and a database with the same name is encountered, the restore operation fails with an error.

# Continue with restores of other selected databases even if one fails

If one database in the instance is not successfully restored, the restore operation continues for all other data that is being restored. When this option is not selected, the restore job stops when the recovery of a resource fails.

#### **Mount Point Prefix**

For **Instant Access** restore operations, specify a mount point prefix for the path where the mount is to be directed.

7. Optional: On the **Apply scripts** page, specify scripts that can be run before or after a job runs. Batch and PowerShell scripts are supported on Windows operating systems while shell scripts are supported on Linux operating systems.

## **Pre-Script**

Select this check box to choose an uploaded script and an application or script server where the pre-script will run. To select an application server, clear the **Use Script Server** check box. To configure scripts and script servers, click **System Configuration** > **Script**.

#### **Post-Script**

Select this option to choose an uploaded script and an application or script server where the post-script will run. To select an application server, clear the **Use Script Server** check box. To configure scripts and script servers, click **System Configuration** > **Script** page.

## Continue job/task on script error

Select this option to continue running the job when the script that is associated with the job fails. When this option is enabled, in the event that a script completes processing with a nonzero return code, the backup or restore job continues to run and the pre-script task status is reported as COMPLETED. If a post-script completes processing with a nonzero return code, the post-script task status is reported as COMPLETED. When this option is not selected, the backup or restore job does not run, and the pre-script or post-script task is reported as FAILED.

Click **Next** to continue.

- 8. On the **Schedule** page, click **Next** to start on-demand jobs after you complete the Snapshot restore wizard. For recurring jobs, enter a name for the job schedule, and specify how often and when to start the restore job.
- 9. On the **Review** page, review your restore job settings.



**Attention:** Review the selected options before you proceed to **Submit** because data will be overwritten when the **Overwrite existing data** application option is selected. You can cancel a restore job when it is in progress, but if the **Overwrite existing data** option is selected, data is overwritten even if you cancel the job.

10. To proceed with the job, click **Submit**. To cancel the job, navigate to **Jobs and Operations** and click the **Schedule** tab. Find the restore job you want to cancel. Click **Actions**, and select **Cancel**.

#### Results

A few moments after you select **Restore**, the **onDemandRestore** job is added to the **Jobs and Operations** > **Running Jobs** pane. Click the record to show the step-by-step details of the operation. You can also download the zipped log file by clicking **Download.zip**. For any other jobs, click the **Running Jobs** or **Job History** tabs and click the job to display its details.

The IP address and port for the restored server can be found in the log file for the restore operation. Navigate to **Jobs and Operations** > **Running Jobs** to find the logs for your restore operation.

For information about restoring data to the original instance, see <u>Restoring to the original instance</u>. For information about restoring your data to an alternative instance, see <u>Restoring to an alternate instance</u>.

## Restoring MongoDB data to the original instance

You can restore a MongoDB instance to the original host and choose between restoring to the latest backup or an earlier MongoDB database backup version. When you restore data to its original instance, you cannot rename it. This restore option runs a full production restoration of data, and existing data is overwritten at the target site if the **Overwrite existing databases** application option is selected.

## Before you begin

Before you create a restore job for MongoDB, ensure that the following requirements are met:

- At least one MongoDB backup job is set up and running successfully. For instructions about setting up a backup job, see "Backing up MongoDB data" on page 189.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is setting up the restore job. For instructions about assigning roles, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275, and "Roles for MongoDB" on page 183.
- Enough disk space is allocated at the target server for the restore operation.
- Dedicated volumes are allocated for file copying.
- The same directory structure and layout are available on both the target and source servers.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

For more information about space requirements, see <u>Space prerequisites for MongoDB protection</u>. For more information about prerequisites and setup, see <u>Prerequisites for MongoDB</u>.

#### **Procedure**

1. In the navigation pane, click **Manage Protection** > **Applications** > **MongoDB** > **Create Restore Job** to open the Snapshot restore wizard.

## Tips:

- You can also start the Snapshot restore wizard by clicking Jobs and Operations > Create Restore
  Job > MongoDB.
- For a running summary of your selections in the Snapshot restore wizard, move the cursor to the ticon.
- If you want to bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the add to restore list icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.

The selected sources are added to the restore list next to the database list. To remove an item from the list source, click the remove from restore list icon next to the item.

- c) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue.

Option	Description
Type of Restore	Select the type of restore job to run.
	On-Demand: Snapshot Performs a one-time restore operation from a snapshot backup.
	On-Demand: Point in Time Performs a one-time restore operation from a specific point-in-time backup.
	Recurring Performs scheduled restore operations of data from the latest restore points.
Restore Location Type	Select a type of location to restore from:  Site  Restores data from a site that is associated with the backup storage server.

Option	Description
	Cloud Offload Restores data that is stored on cloud storage.
	Repository Offload Restores data that is stored on the repository server.
	Cloud Archive Restores data that is archived on cloud storage.
	Repository Archive Restores data that is archived on the repository server.
Select a	If you are restoring data from a site, select one of the following restore locations:
location	<b>Demo</b> Restores data from the demonstration vSnap server that is set up for test purposes.
	<b>Primary</b> Restores data from the vSnap server that is the primary backup destination.
	Secondary Restores data from the vSnap server that is the secondary backup destination.
	If you are restoring data from a cloud or repository server, you do not have to make a selection because the location is already selected.
Date selector	For on-demand restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand restore operations, select a snapshot from the list of available snapshots in the selected date range.
Use alternate vSnap server for the	Select this box to specify an alternative vSnap server when you are restoring a specific restore point from a cloud resource or repository server, and then select a server from the <b>Select alternate vSnap</b> menu.
restore job	When you are restoring data from a restore point that was offloaded to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway for the restore operation.

- 4. On the "Set destination" page, choose **Restore to original instance** and click **Next**.
- 5. On the **Restore method** page, choose the type of restore operation, and click **Next** to continue.

#### Production

To recover an entire instance to the original instance, the preferred method is to choose this option with the overwrite application option. MongoDB instances that are members of a replica set are not started during a production restore operation. This action prevents data from being overwritten when connecting to the replica set.

#### Test

Choose this option to restore data to the same server but using a different port.

#### Instant Access

Choose this option to mount the backup to the application server without restoring the data or overwriting the data.

Click Next to continue.

For test mode or production mode, you can optionally enter a new name for the restored database.

For production mode, you can also specify a new folder for the restored database by expanding the database and entering a new folder name.

6. Optional: On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

In the **Recovery Options** section, the **Recover until end of backup** for MongoDB is selected by default. This option recovers the selected data to the state it was in at the time the backup was created. The recovery operation makes use of the log files that are included in the MongoDB backup.

# **Application Options**

Set the application options:

## Overwrite existing database

Enable this option to allow the restore job to overwrite the selected database. If this option is not selected, the restore job fails when data with the same name is found during the restore process.



**Attention:** Ensure that no other data shares the same local database directory as the original data or the data will be overwritten.

## **Maximum Parallel Streams per Database**

Set the maximum number of parallel data streams from the backup storage per database. This setting applies to each database in the job definition. Multiple databases can still be restored in parallel if the value of the option is set to 1. Multiple parallel streams might speed up restore operations, but high bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring a MongoDB database to its original location by using its original database name.

## **Advanced Options**

Set the advanced job definition options:

## Run cleanup immediately on job failure

This option is selected by default to automatically clean up allocated resources as part of a restore operation if recovery fails.

## Allow session overwrite

Select this option to replace existing databases with the same name during a restore operation. During an instant disk restore operation, the existing database is shut down and overwritten, and then the recovered database is restarted. If this option is not selected and a database with the same name is encountered, the restore operation fails with an error.

## Continue with restores of other selected databases even if one fails

If one database in the instance is not successfully restored, the restore operation continues for all other data that is being restored. When this option is not selected, the restore job stops when the recovery of a resource fails.

# **Mount Point Prefix**

For **Instant Access** restore operations, specify a mount point prefix for the path where the mount is to be directed.

7. Optional: On the **Apply scripts** page, specify scripts that can be run before or after a job runs. Batch and PowerShell scripts are supported on Windows operating systems while shell scripts are supported on Linux operating systems.

# **Pre-Script**

Select this check box to choose an uploaded script and an application or script server where the pre-script will run. To select an application server, clear the **Use Script Server** check box. To configure scripts and script servers, click **System Configuration** > **Script**.

## **Post-Script**

Select this option to choose an uploaded script and an application or script server where the post-script will run. To select an application server, clear the **Use Script Server** check box. To configure scripts and script servers, click **System Configuration** > **Script** page.

## Continue job/task on script error

Select this option to continue running the job when the script that is associated with the job fails. When this option is enabled, in the event that a script completes processing with a nonzero return code, the backup or restore job continues to run and the pre-script task status is reported as COMPLETED. If a post-script completes processing with a nonzero return code, the post-script task status is reported as COMPLETED. When this option is not selected, the backup or restore job does not run, and the pre-script or post-script task is reported as FAILED.

Click **Next** to continue.

- 8. On the **Schedule** page, click **Next** to start on-demand jobs after you complete the Snapshot restore wizard. For recurring jobs, enter a name for the job schedule, and specify how often and when to start the restore job.
- 9. On the **Review** page, review your restore job settings.



**Attention:** Review the selected options before you proceed to **Submit** because data will be overwritten when the **Overwrite existing data** application option is selected. You can cancel a restore job when it is in progress, but if the **Overwrite existing data** option is selected, data is overwritten even if you cancel the job.

10. To proceed with the job, click **Submit**. To cancel the job, navigate to **Jobs and Operations** and click the **Schedule** tab. Find the restore job you want to cancel. Click **Actions**, and select **Cancel**.

## Restoring MongoDB data to an alternative instance

You can select a MongoDB database backup and restore it to an alternative host. You can also choose to restore a database to a different vSnap repository, or you can rename the database. This process creates an exact copy of the instance on a different host.

## Before you begin

Before you create a restore job for MongoDB, ensure that the following requirements are met:

- At least one MongoDB backup job is set up and running successfully. For instructions about setting up a backup job, see "Backing up MongoDB data" on page 189.
- IBM Spectrum Protect Plus roles and resource groups are assigned to the user who is setting up the restore job. For instructions about assigning roles, see <a href="Chapter 13">Chapter 13</a>, "Managing user access," on page 275, and "Roles for MongoDB" on page 183.
- Enough disk space is allocated at the target server for the restore operation.
- Dedicated volumes are allocated for file copying.
- The same directory structure and layout are available on both the target and source servers.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

For restore operations to alternative instances, MongoDB must be at the same version level on the target and host machines.

For more information about space requirements, see <u>Space prerequisites for MongoDB protection</u>. For more information about prerequisites and setup, see <u>Prerequisites for MongoDB</u>.

## **Procedure**

1. In the navigation pane, click **Manage Protection** > **Applications** > **MongoDB** > **Create Restore Job** to open the Snapshot restore wizard.

#### Tips:

You can also start the Snapshot restore wizard by clicking Jobs and Operations > Create Restore
Job > MongoDB.

- For a running summary of your selections in the Snapshot restore wizard, move the cursor to the ticon.
- If you want to bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the add to restore list icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.

The selected sources are added to the restore list next to the database list. To remove an item from the list source, click the remove from restore list icon next to the item.

- c) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue

Option	Description
Type of Restore	Select the type of restore job to run.
	On-Demand: Snapshot Performs a one-time restore operation from a snapshot backup.
	On-Demand: Point in Time Performs a one-time restore operation from a specific point-in-time backup.
	Recurring Performs scheduled restore operations of data from the latest restore points.
Restore Location Type	Select a type of location to restore from:
	Site Restores data from a site that is associated with the backup storage server.  Cloud Offload Restores data that is stored on cloud storage.
	Repository Offload  Restores data that is stored on the repository server.
	Cloud Archive Restores data that is archived on cloud storage.
	Repository Archive  Restores data that is archived on the repository server.
Select a	If you are restoring data from a site, select one of the following restore locations:
location	<b>Demo</b> Restores data from the demonstration vSnap server that is set up for test purposes.
	<b>Primary</b> Restores data from the vSnap server that is the primary backup destination.
	Secondary  Restores data from the vSnap server that is the secondary backup destination.
	If you are restoring data from a cloud or repository server, you do not have to make a selection because the location is already selected.
Date selector	For on-demand restore operations, specify a range of dates to show the available snapshots within that date range.

Option	Description
Restore Point	For on-demand restore operations, select a snapshot from the list of available snapshots in the selected date range.
Use alternate vSnap server for the restore job	Select this box to specify an alternative vSnap server when you are restoring a specific restore point from a cloud resource or repository server, and then select a server from the <b>Select alternate vSnap</b> menu.  When you are restoring data from a restore point that was offloaded to a cloud resource or repository server, a vSnap server is used as a gateway to complete the
	operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway for the restore operation.

4. In the **Set destination** page, choose **Restore to alternate instance** and select the target instance that you want to restore the data to.

The original instance is not selectable because you cannot overwrite the original data when you select **Restore to alternate instance**. You also cannot select instances on different versions levels or instances on the same host as the original instance.

Click **Next** to continue.

- 5. On the **Restore method** page, choose the type of restore operation, and click **Next** to continue.
  - **Test**: In this mode, the agent creates a database by using the data files directly from the vSnap repository. This option is available only when you are restoring data to an alternative instance. Members of replica sets will not be reconfigured after the MongoDB server is started. The server is started as a single-node replica set.
  - **Production**: In this mode, the MongoDB application server first copies the files from the vSnap repository to the target host. The copied data is then used to start the database. MongoDB instances that are members of a replica set are not started during a production restore operation. This action prevents data from being overwritten when connecting to the replica set.
  - **Instant Access**: In this mode, no further action is taken after IBM Spectrum Protect Plus mounts the share. Use the data for custom recovery from the files in the vSnap repository.

For test mode or production mode, you can optionally enter a new name for the restored database.

For production mode, you can also specify a new folder for the restored database by expanding the database and entering a new folder name.

6. Optional: On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

In the **Recovery Options** section, the **Recover until end of backup** for MongoDB is selected by default. This option recovers the selected data to the state it was in at the time the backup was created. The recovery operation makes use of the log files that are included in the MongoDB backup.

# **Application Options**

Set the application options:

# Overwrite existing database

Enable this option to allow the restore job to overwrite the selected database. If this option is not selected, the restore job fails when data with the same name is found during the restore process.



**Attention:** Ensure that no other data shares the same local database directory as the original data or the data will be overwritten.

## **Maximum Parallel Streams per Database**

Set the maximum number of parallel data streams from the backup storage per database. This setting applies to each database in the job definition. Multiple databases can still be restored in parallel if the value of the option is set to 1. Multiple parallel streams might speed

up restore operations, but high bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring a MongoDB database to its original location by using its original database name.

# **Advanced Options**

Set the advanced job definition options:

# Run cleanup immediately on job failure

This option is selected by default to automatically clean up allocated resources as part of a restore operation if recovery fails.

## Allow session overwrite

Select this option to replace existing databases with the same name during a restore operation. During an instant disk restore operation, the existing database is shut down and overwritten, and then the recovered database is restarted. If this option is not selected and a database with the same name is encountered, the restore operation fails with an error.

## Continue with restores of other selected databases even if one fails

If one database in the instance is not successfully restored, the restore operation continues for all other data that is being restored. When this option is not selected, the restore job stops when the recovery of a resource fails.

#### **Mount Point Prefix**

For **Instant Access** restore operations, specify a mount point prefix for the path where the mount is to be directed.

7. Optional: On the **Apply scripts** page, specify scripts that can be run before or after a job runs. Batch and PowerShell scripts are supported on Windows operating systems while shell scripts are supported on Linux operating systems.

# **Pre-Script**

Select this check box to choose an uploaded script and an application or script server where the pre-script will run. To select an application server, clear the **Use Script Server** check box. To configure scripts and script servers, click **System Configuration** > **Script**.

#### **Post-Script**

Select this option to choose an uploaded script and an application or script server where the post-script will run. To select an application server, clear the **Use Script Server** check box. To configure scripts and script servers, click **System Configuration** > **Script** page.

# Continue job/task on script error

Select this option to continue running the job when the script that is associated with the job fails. When this option is enabled, in the event that a script completes processing with a nonzero return code, the backup or restore job continues to run and the pre-script task status is reported as COMPLETED. If a post-script completes processing with a nonzero return code, the post-script task status is reported as COMPLETED. When this option is not selected, the backup or restore job does not run, and the pre-script or post-script task is reported as FAILED.

Click **Next** to continue.

- 8. On the **Schedule** page, click **Next** to start on-demand jobs after you complete the Snapshot restore wizard. For recurring jobs, enter a name for the job schedule, and specify how often and when to start the restore job.
- 9. On the **Review** page, review your restore job settings.



**Attention:** Review the selected options before you proceed to **Submit** because data will be overwritten when the **Overwrite existing data** application option is selected. You can cancel a restore job when it is in progress, but if the **Overwrite existing data** option is selected, data is overwritten even if you cancel the job.

10. To proceed with the job, click **Submit**. To cancel the job, navigate to **Jobs and Operations** and click the **Schedule** tab. Find the restore job you want to cancel. Click **Actions**, and select **Cancel**.

## Using a granular restore operation for MongoDB

You can restore specific MongoDB databases or collections by using a granular restore operation. For a granular restore operation, first run a test restore job and then run the appropriate MongoDB commands.

## Before you begin

If authentication is enabled, you must provide credentials for users so that they can correct permissions on the instance in the test restore operation.

#### **About this task**

The granular restore operation for MongoDB is based on a test mode restore job. When you run the test restore job on IBM Spectrum Protect Plus, and the **mongodump** and **mongorestore** commands on the MongoDB server, you can access individual databases or collections from the recovery source.

Use this procedure to complete either of the following tasks:

- Restore any number of databases by using the mongodump and mongorestore commands for the databases that you require.
- Restore any number of collections by using the **mongodump** and **mongorestore** commands for the collections that you require.

#### **Procedure**

- 1. In the navigation pane, click Manage Protection > Applications > MongoDB.
- 2. Click **Create Restore Job** to open the restore wizard. MongoDB is automatically selected.
- 3. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the add to restore list icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.
    - The selected sources are added to the restore list next to the database list. To remove an item from the list source, click the remove from restore list icon next to the item.
  - c) Click Next to continue.
- 4. On the **Set destination** page, choose **Restore to alternate instance**, and select the target instance that you want to restore the data to.

You cannot select the original instance is not selectable as you cannot overwrite the original data when you select **Restore to alternate instance**. Instances on different versions levels cannot be selected. Other instances on the same host as the original instance, cannot be selected either.

Click Next to continue.

- 5. On the **Restore method** page, select **Test**, and click **Next** to continue with the test restore process.
- 6. Proceed through the restore wizard pages and select the required options.
- 7. On the **Review** page, review your restore job settings.



**Attention:** Review the selected options before you proceed to **Submit** because data will be overwritten when the **Overwrite existing data** application option is selected. You can cancel a restore job when it is in progress, but if the **Overwrite existing data** option is selected, data is overwritten even if you cancel the job.

- 8. Log on to the MongoDB server to which the test restore job is directed.
- 9. Run the MongoDB system command ps <code>-ef | grep mongod</code> to find the temporary recovery MongoDB instance location.
- 10. Run the MongoDB mongodump command to create a dump file of any specific database or collection.

Use the appropriate command. The first command is for a database and the second command is for a collection:

```
mongodump --host <hostname> --port <port> --db <dbname> <dumpfolder>
Or,
```

```
mongodump --host <hostname> --port <port> --collection <collectionname> <dumpfolder>
```

11. Run the **mongorestore** command to restore the dump file into any MongoDB instance. Choose either the original MongoDB instance that the backup was created for, or any alternative instance.

Use the appropriate command. The first command is for a database and the second command is for a collection:

```
mongorestore --host <hostname> --port <port> --db <dbname> <dumpfolder>\<dbname>
Or,

mongorestore --host <hostname> --port <port> --collection <collectionname> <dumpfolder> \<dbname>
```

- 12. When the database or collection restore operation finishes, go to **Jobs and Operations** > **Active Resources**.
- 13. Click **Actions** > **Cancel Restore** to end the granular restore procedure.

# **Backing up and restoring SQL Server data**

To protect content on a SQL Server server, first register the SQL Server instance so that IBM Spectrum Protect Plus recognizes it. Then create jobs for backup and restore operations.

#### **System requirements**

Ensure that your SQL Server environment meets the system requirements in <u>"Microsoft SQL Server requirements"</u> on page 38.

#### **Registration and authentication**

The default security policy uses the Windows NTLM protocol, and the user identity format follows the default *domain*\name format.

When you are using Windows group policy objects (GPO), the group policy object setting, **Network security: LAN Manager** authentication level must be set correctly. Set it with one of the following options:

- Not Defined
- Send NTLMv2 response only
- Send NTLMv2 response only. Refuse LM
- Send NTLMv2 response only. Refuse LM & NTLM

# Adding a SQL Server application server

When a SQL Server application server is added, an inventory of the instances and databases that are associated with the application server is captured and added to IBM Spectrum Protect Plus. This process enables you to complete backup and restore jobs, as well as run reports.

#### **Procedure**

To add a SQL Server host, complete the following steps.

1. In the navigation pane, click Manage Protection > Applications > SQL > Backup.

- 2. Click Manage Application Servers.
- 3. Click Add Application Server.
- 4. Populate the fields in the **Application Properties** pane:

#### **Host Address**

Enter the resolvable IP address or a resolvable path and machine name.

# Use existing user

Enable to select a previously entered user name and password for the provider.

#### UserID

Enter your user name for the provider. The user identity follows the default *domain*\name format if the virtual machine is attached to a domain. The format *local* \_administrator is used if the user is a local administrator.

For Kerberos-based authentication only, the user identity must be specified in the username@FQDN format. The user name must be able to authenticate using the registered password to obtain a ticket-granting ticket (TGT) from the key distribution center (KDC) on the domain that is specified by the fully qualified domain name.

#### **Password**

Enter your password for the provider.

#### **Maximum concurrent databases**

Set the maximum number of databases to back up concurrently on the server. Server performance is impacted when backing up a large number of databases concurrently, as each database utilizes multiple threads and consumes bandwidth when copying data. Use this option to control the impact on server resources and minimize the impact on production operations.

5. Click **Save**. IBM Spectrum Protect Plus confirms a network connection, adds the application server to the IBM Spectrum Protect Plus database, and then catalogs the instance.

If a message appears indicating that the connection is unsuccessful, review your entries. If your entries are correct and the connection is unsuccessful, contact a system administrator to review the connections.

#### What to do next

After you add the SQL Server application server, complete the following action:

Action	How to
Assign user permissions to the application server.	See <u>"Creating a role" on page 280</u> .

#### **Related concepts**

"Managing user access" on page 275

By using role-based access control, you can set the resources and permissions available to IBM Spectrum Protect Plus user accounts.

#### **Related tasks**

"Backing up SQL Server data" on page 207

Use a backup job to back up SQL Server environments with snapshots.

"Restoring SQL Server data" on page 210

Use a restore job to restore a Microsoft SQL Server environment from snapshots. After you run IBM Spectrum Protect Plus Instant Disk Restore jobs, your SQL Server clones can be used immediately. IBM Spectrum Protect Plus catalogs and tracks all cloned instances.

# **Detecting SQL Server resources**

SQL Server resources are automatically detected after the application server is added to IBM Spectrum Protect Plus. However, you can run an inventory job to detect any changes that occurred since the application server was added.

#### **Procedure**

To run an inventory job, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Applications > SQL > Backup.
- 2. In the list of SQL Server instances, select an instance or click the link for the instance to navigate to the resource that you want. For example, if you want to run an inventory job for an individual database in the instance, click the instance link and then select a virtual machine.
- 3. Click Run Inventory.

## Testing the connection to a SQL Server application server

You can test the connection to a SQL Server host. The test function verifies communication with the host and tests DNS settings between the IBM Spectrum Protect virtual appliance and the host.

#### **Procedure**

To test the connection, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Applications > SQL > Backup.
- 2. Click Manage Application Servers.
- 3. In the list of hosts, click **Test** in the **Actions** menu for the host.

# **Backing up SQL Server data**

Use a backup job to back up SQL Server environments with snapshots.

#### Before you begin

During the initial base backup, IBM Spectrum Protect Plus creates a new vSnap LUN volume and creates an NTFS share on that iSCSI LUN. During incremental backups, the previously created volume is reused. The IBM Spectrum Protect Plus agent maps the LUN to the SQL Server server and mounts the NTFS volume to where the backup is completed. If log backups are enabled IBM Spectrum Protect Plus creates a separate vSnap volume and creates a CIFS on that volume. Log backup transaction files are copied to this share according to the schedule created for log backup.

When the backup is complete, the IBM Spectrum Protect Plus agent unmounts the share from the SQL Server server and creates a vSnap snapshot of the backup volume.

Review the following information:

- Before an IBM Spectrum Protect Plus user can implement backup and restore operations, roles and
  resource groups must be assigned to the user. Grant users access to resources and backup and restore
  operations through the **Accounts** pane. For more information, see <a href="Chapter 13">Chapter 13</a>, "Managing user access,"
  on page 275.
- Microsoft iSCSI Initiator must be enabled and running on the Windows server. An iSCSI route must be enabled between the SQL system and vSnap server. For more information, see Microsoft iSCSI Initiator Step-by-Step Guide.
- Avoid configuring log backup for a single SQL database through multiple backup jobs. Logs are truncated during log backup operations. If a single SQL database is added to multiple job definitions with log backup enabled, a log backup from one job will truncate a log before it is backed up by the next job. This might cause point-in-time restore jobs to fail.

- IBM Spectrum Protect Plus does not support log backup of Simple recovery models.
- Prior to copying logs to vSnap, IBM Spectrum Protect Plus uses the backup folder configured for the SQL server instance as the staging area to collect logs. The volume where this folder is located must have sufficient space available to hold all of the transaction logs between backup jobs. The staging area can be modified by changing the backup folder configuration using SQL Server Management Studio (SSMS).
- Failover of a SQL cluster instance during backup is not supported.
- If you plan to back up a large number of databases, you might have to increase the number of maximum worker threads on each associated SQL Server instance to ensure that backup jobs are completed successfully. The default value for maximum worker threads is 0. The server automatically determines the maximum worker threads value based on the number of processors available to the server. SQL Server uses the threads from this pool for network connections, database checkpoints, and queries. Additionally, a backup of each database requires one additional thread from this pool. If you have a large number of databases in a backup job, the default max worker threads might not be enough to back up all of the databases and the job will fail. For more information about increasing the maximum worker threads option, see Configure the max worker threads Server Configuration Option.
- When a log backup of a secondary SQL Always On database fails with the following error, the backup preference of the availability group must be changed to Primary:

```
Log backup for database 'DatabaseName' on a secondary replica failed because a synchronization point could not be established on the primary database.
```

Changing the preference to Primary will back up the log from the primary replica. After a successful log backup of the primary replica is completed, the backup preference can be changed.

**Note:** Due to limitations with the Volume Shadow Copy Services (VSS) framework, leading spaces, trailing spaces, and unprintable characters should not be used in database names. For more information, see <a href="https://support.microsoft.com/en-sg/help/2014054/backing-up-a-sql-server-database-using-a-vss-backup-application-may-fa">https://support.microsoft.com/en-sg/help/2014054/backing-up-a-sql-server-database-using-a-vss-backup-application-may-fa</a>

Take the following actions:

- Register the SQL Servers that you want to back up. For more information, see <u>"Adding a SQL Server</u> application server" on page 205.
- Configure SLA policies. For more information, see "Create backup policies" on page 70.
- Before setting up and running SQL backup jobs you must configure the Shadow Copy storage settings
  for the volumes where your SQL databases are located. This setting is configured once per volume. If
  new databases are added to the job, the setting must configured for any new volumes containing SQL
  databases. In Windows Explorer, right-click the source volume and select the Shadow Copies tab. Set
  the Maximum size to No limit or a reasonable size depending on the source volume size and I/O
  activities, then click OK. The shadow copy storage area must be on the same volume or another
  available volume during the time of backup.

# **Procedure**

ı

To define an SQL backup job, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Applications > SQL.
- 2. Select a SQL Server instance to back up.
  - Use the search function to search for available instances and toggle the displayed instances through the **View** filter. The available options are **Standalone/Failover Cluster** and **Always On**.
- 3. Click **Select an SLA Policy** to add one or more SLA policies that meet your backup data criteria to the job definition.
- 4. To create the job definition by using default options, click Save.
  The job runs as defined by the SLA policies that you selected. To run the job manually, click Jobs and Operations > Schedule. Select the job and click Actions > Start.

**Tip**: The **Run**button is only enabled for a single database backup, and the database must have an SLA policy applied.

5. To edit options before you create the job definition, click **Select Options**. Set the job definition options.

# **Enable Log Backup**

Select to enable IBM Spectrum Protect Plus to back up transaction logs and then protect the underlying disks.

IBM Spectrum Protect Plus automatically truncates post log backups of databases that it backs up. If database logs are not backed up with IBM Spectrum Protect Plus, logs are not truncated by IBM Spectrum Protect Plus and must be managed separately.

When a SQL backup job completes with log backups enabled, all transaction logs up to the point of the job completing are purged from the SQL Server server. Log purging occurs only if the SQL Backup job completes successfully. If log backups are disabled during a rerun of the job, log purging does not occur.

If a source database is overwritten, all old transaction logs up to that point are placed in a "condense" directory once the restoration of the original database completes. When the next run of the SQL Backup job completes, the contents of the condense folder is removed.

To complete log backups, the SQL Server agent service user must be a local Windows administrator and must have the sysadmin permission enabled to manage SQL Server agent jobs. The agent will use that administrator account to enable and access log backup jobs. The IBM Spectrum Protect Plus SQL Server agent service user must also be the same as the SQL Server service and SQL Server agent service account for every SQL Server instance to be protected.

SQL log files are temporarily stored in a local staging area before they are copied to a CIFS share. The SQL server default backup destination serves as the staging area and must have enough free space to temporarily store the transaction log files before they can be copied to the CIFS share.

To enable log backup schedule creation for multiple databases on the same SQL Server instance, ensure that all databases are added to the same SLA policy.

When this option is selected, point-in-time restore options are available for SQL restore operations.

#### **Maximum Parallel Streams per Database**

Set the maximum data stream per database to the backup storage. This setting applies to each database in the job definition. Multiple databases can be backed up in parallel if the value of the option is set to **1**. Multiple parallel streams might improve backup speed, but high bandwidth consumption might affect overall system performance.

- 6. When you are satisfied that the job-specific information is correct, click **Save**.
  - The job runs as defined by your SLA policy, or can be run manually from the Job Monitor pane.
- 7. To configure additional options, click the **Policy Options** field that is associated with the job in the **SLA Policy Status** section. Set the additional policy options:

#### **Pre-scripts and post-scripts**

Run a pre-script or a post-script. Pre-scripts and post-scripts are scripts that can be run before or after a job runs. Batch and PowerShell scripts are supported.

In the **Pre-script** or **Post-script** section, select an uploaded script and an application or script server where the script will run. To select an application server where the script will run, clear the **Use Script Server** check box. Scripts and script servers are configured on the **System Configuration** > **Script** page.

To continue running the job if the script associated with the job fails, select **Continue job/task on script error**.

When this option is enabled, if a pre-script or post-script completes processing with a non-zero return code, the backup or restore operation is attempted and the pre-script task status is reported as COMPLETED. If a post-script completes with a non-zero return code, the post-script task status is reported as COMPLETED.

When this option is disabled, the backup or restore is not attempted, and the pre-script or post-script task status is reported as FAILED.

#### **Exclude Resources**

Exclude specific resources from the backup job through single or multiple exclusion patterns. Resources can be excluded through an exact match or with wildcard asterisks specified before the pattern (\*test) or after the pattern (test\*).

Multiple asterisk wildcards are also supported in a single pattern. Patterns support standard alphanumeric characters as well as the following special characters: - \_ and \*.

Separate multiple filters with a semicolon.

## **Force Full Backup of Resources**

Force base backups operations for specific virtual machines or databases in the backup job definition. Separate multiple resources with a semicolon.

8. To save any additional options that you configured, click **Save**.

#### What to do next

After you create the backup job definition, complete the following action:

Action	How to
Create a SQL Restore job definition.	See "Restoring SQL Server data" on page 210.

#### **Related concepts**

"Configuring scripts for backup and restore operations" on page 234

Prescripts and postscripts are scripts that can be run before or after backup and restore jobs run at the job level. Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts are created locally, uploaded to your environment through the **Script** page, and then applied to job definitions.

#### **Related tasks**

"Starting jobs" on page 232

You can run any job on demand, even if the job is set to run on a schedule.

# **Restoring SQL Server data**

Use a restore job to restore a Microsoft SQL Server environment from snapshots. After you run IBM Spectrum Protect Plus Instant Disk Restore jobs, your SQL Server clones can be used immediately. IBM Spectrum Protect Plus catalogs and tracks all cloned instances.

# Before you begin

Complete the following prerequisites:

- Create and run an SQL backup job. For instructions, see "Backing up SQL Server data" on page 207.
- Before an IBM Spectrum Protect Plus user can restore data, the appropriate roles and resource groups must be assigned to the user. Grant users access to resources and backup and restore operations by using the **Accounts** pane. For instructions, see Chapter 13, "Managing user access," on page 275.
- If you are planning to run a point-in-time recovery, ensure that both the restore target SQL instance service and the IBM Spectrum Protect Plus SQL Server service use the same user account.

Review the following restrictions and considerations:

• If you are planning to run a production restore operation to an SQL Server failover cluster, the root volume of the alternative file path must be eligible to host database and log files. The volume should belong to the destination SQL Server cluster server resource group, and be a dependency of the SQL Server cluster server.

- You cannot restore data to an NTFS or FAT compressed volume because of SQL Server database restrictions. For more information, see <u>Description of support for SQL Server databases on compressed volumes</u>.
- If you are planning to restore data to an alternative location, the SQL Server destination must be running the same version of SQL Server or a later version. For more information, see Compatibility Support.
- When you are restoring data to a primary instance in an SQL Always On Availability Group environment, the database is added to the target Always On database group. After the primary restore operation, the secondary database is seeded by the SQL server in environments where automatic seeding is supported (Microsoft SQL Server 2016 and later). The database is then enabled on the destination availability group. The synchronization time depends on the amount of data that is being transferred and the connection between the primary and secondary replicas.

If automatic seeding is not supported or is not enabled, a secondary restore from the restore point with the shortest Log Sequence Number (LSN) gap of the primary instance must be completed. Log backups with the latest point-in-time restore point that is created by IBM Spectrum Protect Plus must be restored if the log backup was enabled on the primary instance. The secondary database restore operation is completed in the RESTORING state and you must issue the **T-SQL** command to add the database to the target group. For more information, see Transact-SQL Reference (Database Engine).

• When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

#### **About this task**

Instant Disk Restore uses the iSCSI protocol to immediately mount LUNs without transferring data. Databases for which snapshots were taken are cataloged and instantly recoverable with no physical transfer of data.

The following restore modes are supported:

#### **Instant access mode**

In instant access mode, no further action is taken after mounting the share. Users can complete any custom recovery by using the files in the vSnap volume. An instant access restore of an Always On database is restored to the local destination instance.

#### **Test mode**

In test mode, the agent creates a new database by using the data files directly from the vSnap volume.

# **Production mode**

In production mode, the agent first restores the files from the vSnap volume back to primary storage and then creates the new database by using the restored files.

#### **Procedure**

To define an SQL restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Applications** > **SQL** > **Create Restore Job** to open the "Snapshot restore" wizard.

## Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore
   Job > SQL.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, take the following actions:

a) Click a source in the list to show the databases that are available for restore operations. You can toggle the displayed sources to show either SQL Server instances in a stand-alone or cluster environment or Always On availability groups by using the **View** filter.

You can also use the search function to search for databases in the instances or availability groups.

b) Click the plus icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.

The selected sources are added to the restore list next to the database list. To remove an item from the list source, click the minus icon next to the item.

- c) Click Next to continue.
- 3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue. Some fields are not displayed until you select a related field.

Option	Description
Restore	Select the type of restore job:
Туре	On-demand: Snapshot Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard
	Recurring Creates a repeating point-in-time restore job that runs on a schedule.
Restore	Select a type of location from which to restore data:
Location Type	Site  The site where snapshots were backed up. The site is defined on the System  Configuration > Site pane.
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a	If you are restoring data from a site, select one of the following restore locations:
location	<b>Demo</b> The demonstration site from which to restore snapshots.
	<b>Primary</b> The primary site location from which to restore snapshots.
	Secondary The secondary site location from which to restore snapshots.

Option	Description
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.
server for the restore job	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.

4. On the **Set destination** page, specify where you want to restore the database and click **Next**.

## Restore to original instance

Select this option to restore the database to the original instance.

## **Restore to primary instance**

For restore operations in an SQL Always On environment, select this option to restore the database to the primary instance of the Always On Availability Group. The database is added back to the group.

#### Restore to alternate instance

Select this option to restore the database to a local destination that is different from the original instance, and then select the alternative location from the list of available servers.

For restore operations in an SQL Always On environment in test mode, the source availability database is restored to the selected target instance.

For restore operations in an SQL Always On environment in production mode, the restored database is added to the target availability group if the destination instance is a primary replica. If the destination instance is a secondary replica of the target availability group, the database is restored to the secondary replica and left in restoring state.

If the automatic seeding option is enabled for the destination availability group, the secondary database file paths are synchronized with the primary database. If the primary database log is not truncated, the secondary database can be added to the availability group by SQL.

5. On the **Restore method** page, set the restore job to run in test, production, or instant access mode by default.

For test or production mode, you can optionally enter a new name for the restored database.

For production mode, you can also specify a new folder for the restored database by expanding the database and entering a new folder name.

Click Next to continue.

After the job is created, you can run it in test, production, or instant access mode in the **Job Sessions** pane.

6. On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

# **Recovery Options**

Set the following point-in-time recovery options:

## No Recovery

Set the selected database to a RESTORING state. If you are managing transaction log backups without using IBM Spectrum Protect Plus, you can manually restore log files, and add the database to an availability group, assuming that the LSN of the secondary and primary database copies meets the criteria.

**Restriction:** The **No Recovery** option does not support production mode restore operations to SQL Always On groups.

# Recover until end of backup

Restore the selected database to the state at the time that the backup was created.

# Recover until specific point in time

When log backup is enabled by using an SQL backup job definition, point-in-time restore options will be available when you create an SQL restore job definition. Select one of the following options:

- By Time. Select this option to configure a point-in-time recovery from a specific date and time.
- By Transaction ID. Select this option to configure a point-in-time recovery by transaction ID.

In a stand-alone restore operation, IBM Spectrum Protect Plus finds the restore points that directly proceed and follow the selected point in time. During the recovery, the older data backup volume and the newer log backup volume are mounted. If the point in time is after the last backup operation, a temporary restore point is created.

When you run restore operations in an SQL Always On environment in test mode, the restored database will join the instance where the availability group resides.

When you run restore operations in an SQL Always On environment in production mode, the restored primary database is joined to the availability group. If the automatic seeding option is enabled for the destination availability group, the secondary database file paths are synchronized with the primary database. If the primary database log is not truncated, the secondary database can be added to the availability group by SQL.

#### **Application Options**

Set the application options:

## Overwrite existing database

Enable the restore job to overwrite the selected database. By default, this option is not enabled.

**Tip:** Before you run restore operations in an SQL Always On environment by using the production mode with the **Overwrite existing database** option, ensure that the database is not present on the replicas of the target availability group. To do so, you must manually clean up the original databases (to be overwritten) from all replicas of the target availability group.

## **Maximum Parallel Streams per Database**

Set the maximum number of parallel data streams from the backup storage per database. This setting applies to each database in the job definition. If the value of the option is set to 1, multiple databases can still be restored in parallel. Multiple parallel streams might improve restore speed, but high bandwidth consumption might affect overall system performance.

This option is applicable only when you restore an SQL Server database to its original location using its original database name.

# **Advanced Options**

Set the advanced job definition options:

# Run cleanup immediately on job failure

Automatically clean up allocated resources as part of a restore operation if the recovery fails.

#### Allow session overwrite

Select this option to replace an existing database with a database of the same name during recovery. When an Instant Disk Restore is performed for a database and another database with

the same name is already running on the destination host or cluster, IBM Spectrum Protect Plus shuts down the existing database before starting up the recovered database. If this option is not selected, the restore job fails when IBM Spectrum Protect Plus detects a running database with the same name.

#### Continue with restores of other databases even if one fails

Toggle the recovery of a resource in a series if the previous resource recovery fails. If this option is not enabled, the restore job stops if the recovery of a resource fails.

## **Protocol Priority (Instant Access only)**

If more than one storage protocol is available, select the protocol to take priority in the job. The available protocols are **iSCSI** and **Fibre Channel**.

#### **Mount Point Prefix**

For instant access restore operations, specify the prefix for the path where the mount point is to be directed.

7. Optional: On the Apply scripts page, specify scripts that can be run before or after an operation runs at the job level. Batch and PowerShell scripts are supported.

## **Pre-Script**

Select this check box to choose an uploaded script and an application or script server where the pre-script will run. To select an application server where the pre-script will run, clear the **Use** Script Server check box. Scripts and script servers are configured on the System Configuration > Script page.

#### **Post-Script**

Select this option to choose an uploaded script and an application or script server where the postscript will run. To select an application server where the post-script will run, clear the **Use Script** Server check box. Scripts and script servers are configured on the System Configuration > Script page.

## **Continue job/task on script error**

Select this check box to continue running the job if the script that is associated with the job fails.

When you select this check box, if a pre-script or post-script completes processing with a nonzero return code, the backup or restore operation is attempted and the pre-script task status is reported as COMPLETED. If a post-script completes processing with a nonzero return code, the post-script task status is reported as COMPLETED.

If you clear this check box, the backup or restore operation is not attempted, and the pre-script or post-script task status is reported as FAILED.

- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click Next.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

#### Results

An on-demand job begins after you click **Submit**, and the **onDemandRestore** record is added to the **Job** Sessions pane shortly. To view progress of the restore operation, expand the job. You can also download

the log file by clicking the download icon 🤷 .



A recurring job will begin at the scheduled start time when you start the schedule in the **Jobs and Operations** > **Schedule** page.

All running jobs are viewable in the **Jobs and Operations** > **Running Jobs** page.

# **Related concepts**

"Configuring scripts for backup and restore operations" on page 234

Prescripts and postscripts are scripts that can be run before or after backup and restore jobs run at the job level. Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts are created locally, uploaded to your environment through the **Script** page, and then applied to job definitions.

#### **Related tasks**

"Adding a SQL Server application server" on page 205

When a SQL Server application server is added, an inventory of the instances and databases that are associated with the application server is captured and added to IBM Spectrum Protect Plus. This process enables you to complete backup and restore jobs, as well as run reports.

"Backing up SQL Server data" on page 207

Use a backup job to back up SQL Server environments with snapshots.

# **Backing up and restoring Oracle data**

To protect Oracle content, first register the Oracle instance so that IBM Spectrum Protect Plus recognizes it. Then create jobs for backup and restore operations.

Ensure that your Oracle environment meets the system requirements in <u>"Oracle requirements" on page</u> 34.

# Adding an Oracle application server

When an Oracle application server is added, an inventory of the instances and databases that are associated with the application server is captured and added to IBM Spectrum Protect Plus. This process enables you to complete backup and restore jobs, as well as run reports.

#### **Procedure**

To register an Oracle application server, complete the following steps.

- 1. In the navigation pane, click Manage Protection > Applications > Oracle > Backup.
- 2. Click Manage Application Servers.
- 3. Click **Add Application Server** to add the host machine.
- 4. In the **Application Properties** pane, enter the host address.

The host address is a resolvable IP address, or a resolvable path and machine name.

## 5. Select **User** or **SSH key**.

Option	Description
User	Click this option to specify an existing user or enter a user ID and password. The user must have <b>sudo</b> privileges set up. Populate the fields as follows:
	Use existing user  Select this check box to use a previously entered user name and password for the application server. Select a user name from the Select user list.
	UserID  Enter your user name for the application server. If the virtual machine is attached to a domain, the user identity follows the default domain\name format. If the user is a local administrator, use the local_administrator format.
	For Kerberos-based authentication only, the user identity must be specified in the username@FQDN format. The user name must be able to authenticate using the registered password to obtain a ticket-granting ticket (TGT) from the key distribution center (KDC) on the domain that is specified by the fully qualified domain name.
	Password Enter your password for the application server.

Option	Description
SSH Key	Click this option to use an SSH key. Select a key from the <b>Select a SSH key</b> list.

- 6. To protect multithreaded databases in Oracle 12c and later versions, provide credentials for the databases:
  - a) Click **Get databases** to detect and list the Oracle databases on the host server that you are adding. Each Oracle database is listed with its name, status, and an indication of whether credentials were previously specified for the database.
  - b) For each multithreaded database that you want to protect, click **Set Credential** and specify the user ID and password. Alternatively, you can select an existing user from the **Select user** list. You must specify the credentials of an Oracle database user who has SYSDBA privileges.
- 7. In **Maximum concurrent databases**, set the maximum number of databases to back up concurrently on the server.
  - Server performance is impacted when many databases are backed up concurrently, as each database utilizes multiple threads and consumes bandwidth when copying data. Use this option to control the impact on server resources and minimize the impact on production operations.
- 8. Click **Save**. IBM Spectrum Protect Plus confirms a network connection, adds the application server to the IBM Spectrum Protect Plus database, and then catalogs the instance.
  - If a message appears indicating that the connection is unsuccessful, review your entries. If your entries are correct and the connection is unsuccessful, contact a system administrator to review the connections.

#### What to do next

After you add the Oracle application server, complete the following action:

Action	How to
Assign user permissions to the application server.	See <u>"Creating a role" on page 280</u> .

# **Related concepts**

"Managing user access" on page 275

By using role-based access control, you can set the resources and permissions available to IBM Spectrum Protect Plus user accounts.

#### **Related tasks**

"Backing up Oracle data" on page 218

Use a backup job to back up Oracle environments with snapshots.

# "Restoring Oracle data" on page 220

Use a restore job to restore an Oracle environment from snapshots. IBM Spectrum Protect Plus creates a vSnap clone from the version that is selected during the job definition creation and creates a Network Files System (NFS) share. The IBM Spectrum Protect Plus agent then mounts the share on the Oracle server where the restore job is to be run. For Oracle Real Application Clusters (RAC), the restore job is run on all nodes in the cluster.

# **Detecting Oracle resources**

Oracle resources are automatically detected after the application server is added to IBM Spectrum Protect Plus. However, you can run an inventory job to detect any changes that occurred since the application server was added.

# **Procedure**

To run an inventory job, complete the following steps:

1. In the navigation pane, click Manage Protection > Applications > Oracle > Backup.

- 2. In the list of Oracle instances, select an instance or click the link for the instance to navigate to the resource that you want. For example, if you want to run an inventory job for an individual database in the instance, click the instance link and then select a virtual machine.
- 3. Click Run Inventory.

# Testing connection to an Oracle application server

You can test the connection to an Oracle host. The test function verifies communication with the host and tests DNS settings between the IBM Spectrum Protect virtual appliance and the host.

#### **Procedure**

To test the connection, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Applications > Oracle > Backup.
- 2. Click Manage Application Servers.
- 3. In the list of hosts, click **Test** in the **Actions** menu for the host.

# **Backing up Oracle data**

Use a backup job to back up Oracle environments with snapshots.

## Before you begin

Review the following information:

- To ensure that file system permissions are retained correctly when IBM Spectrum Protect Plus moves Oracle data between servers, ensure that the user and group IDs of the Oracle users (for example, oracle, oinstall, dba) are consistent across all the servers. Refer to Oracle documentation for recommended uid and gid values.
- If an Oracle Inventory job runs at the same time or short period after an Oracle backup job, copy errors might occur because of temporary mounts that are created during the backup job. As a best practice, schedule Oracle Inventory jobs so that they do not overlap with Oracle backup jobs.
- Avoid configuring log backup for a single Oracle database by using multiple backup jobs. If a single
  Oracle database is added to multiple job definitions with log backup enabled, a log backup from one job
  could truncate a log before it is backed up by the next job. This might cause point-in-time restore jobs
  to fail.
- Point-in-time recovery is not supported when one or more data files are added to the database in the period between the chosen point-in-time and the time that the preceding backup job ran.

Take the following actions:

- Before an IBM Spectrum Protect Plus user can implement backup and restore operations, roles and resource groups must be assigned to the user. Grant users access to resources and backup and restore operations through the **Accounts** pane. For more information, see <a href="#">Chapter 13</a>, "Managing user access," on page 275.
- Register the providers that you want to back up. For more information, see <u>"Adding an Oracle</u> application server" on page 216.
- Configure SLA policies. For more information, see "Create backup policies" on page 70.

#### **About this task**

During the initial base backup, IBM Spectrum Protect Plus creates a vSnap volume and an NFS share. During incremental backups, the previously created volume is reused. The IBM Spectrum Protect Plus agent mounts the share on the Oracle server where the backup is to be completed.

In the case of Oracle Real Application Clusters (RAC), the backup is completed from any one node in the cluster. When the backup is complete, the IBM Spectrum Protect Plus agent unmounts the share from the Oracle server and creates a vSnap snapshot of the backup volume.

IBM Spectrum Protect Plus can protect multithreaded databases in Oracle 12c and later versions. For instructions about enabling IBM Spectrum Protect Plus to protect multithreaded databases, see <u>"Adding an Oracle application server"</u> on page 216.

#### **Procedure**

To define an Oracle backup job, complete the following steps:

- 1. In the navigation pane, click Manage Protection > Applications > Oracle.
- 2. Select Oracle homes, databases, and ASM diskgroups to back up. Use the search function to search for available instances.
- 3. Click **Select an SLA Policy** to add one or more SLA policies that meet your backup data criteria to the job definition.
- 4. To create the job definition by using default options, click **Save**.

The job runs as defined by the SLA policies that you selected. To run the job manually, click **Jobs and Operations** > **Schedule**. Select the job and click **Actions** > **Start**.

**Tip**: The **Run** button is only enabled for a single database backup, and the database must have an SLA policy applied.

5. To edit options before you create the job definition, click **Select Options**. Set the job definition options.

# **Enable Log Backup**

**Enable Log Backup** must be selected to allow for Oracle point-in-time restore.

Select **Enable Log Backup** to permit IBM Spectrum Protect Plus to automatically create a log backup volume and mount it to the application server. IBM Spectrum Protect Plus then automatically discovers the location of the existing primary archived log and uses cron to configure a scheduled job. The scheduled job completes a transaction log backup from the primary location to that log backup volume at the frequency specified through the **Frequency** setting.

The **Frequency** can be set to a value independent of the database backup frequency specified in the SLA Policy settings. For example, the SLA Policy may be configured to back up the database once per day while the log backup frequency could be set to once per 30 minutes.

For Oracle RAC, IBM Spectrum Protect Plus mounts the volume and configures the cron job on each of the cluster nodes. When the schedule is triggered, the jobs internally coordinate to ensure that any one active node completes the log backup and the other nodes take no action.

IBM Spectrum Protect Plus automatically manages the retention of logs in its own log backup volume based on the retention settings in the SLA policy.

Select **Truncate source logs after successful backup** to automatically delete older archived logs from the database's primary archived log location. If the option is cleared, archived logs on the primary log destination are not deleted, and Database Administrators must continue to manage those logs using their existing log retention policies. If the option is selected, IBM Spectrum Protect Plus deletes older unneeded archived logs from the primary log location at the end of every successful database backup.

When the option **Truncate source logs after successful backup** is selected, set the retention of primary logs through the **Primary log retention in days** setting. This setting controls the quantity of archived logs that are retained in the primary archived log locations. For example, if **Primary log retention in days** is set to **3**, IBM Spectrum Protect Plus deletes all archived logs older than three days from the primary archived log location at the end of every successful database backup.

#### **Maximum Parallel Streams per Database**

Set the maximum data stream per database to the backup storage. This setting applies to each database in the job definition. Multiple databases can be backed up in parallel if the value of the option is set to **1**. Multiple parallel streams might improve backup speed, but high bandwidth consumption might affect overall system performance.

- 6. When you are satisfied that the job-specific information is correct, click Save.
- 7. To configure additional options, click the **Policy Options** field that is associated with the job in the **SLA Policy Status** section. Set the additional policy options:

#### **Pre-scripts and Post-scripts**

Run a pre-script or a post-script. Pre-scripts and post-scripts are scripts that can be run before or after a job runs at the job level. Windows-based machines support Batch and PowerShell scripts while Linux-based machines support shell scripts.

In the **Pre-script** or **Post-script** section, select an uploaded script and an application or script server where the script will run. To select an application server where the script will run, clear the **Use Script Server** check box. Scripts and script servers are configured through the **System Configuration** > **Script** page.

To continue running the job if the script associated with the job fails, select **Continue job/task on script error**.

When this option is enabled, if a pre-script or post-script completes processing with a non-zero return code, the backup or restore operation is attempted and the pre-script task status is reported as COMPLETED. If a post-script completes with a non-zero return code, the post-script task status is reported as COMPLETED.

When this option is disabled, the backup or restore is not attempted, and the pre-script or post-script task status is reported as FAILED.

#### **Exclude Resources**

Exclude specific resources from the backup job through single or multiple exclusion patterns. Resources can be excluded through an exact match or with wildcard asterisks specified before the pattern (\*test) or after the pattern (test\*).

Multiple asterisk wildcards are also supported in a single pattern. Patterns support standard alphanumeric characters as well as the following special characters: - and \*.

Separate multiple filters with a semicolon.

# **Force Full Backup of Resources**

Force base backup operations for specific virtual machines or databases in the backup job definition. Separate multiple resources with a semicolon.

#### What to do next

After you create the backup job definition, complete the following action:

Action	How to
Create an Oracle Restore job definition.	See <u>"Restoring Oracle data" on page 220</u> .

#### **Related concepts**

"Configuring scripts for backup and restore operations" on page 234

Prescripts and postscripts are scripts that can be run before or after backup and restore jobs run at the job level. Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts are created locally, uploaded to your environment through the **Script** page, and then applied to job definitions.

# **Restoring Oracle data**

Use a restore job to restore an Oracle environment from snapshots. IBM Spectrum Protect Plus creates a vSnap clone from the version that is selected during the job definition creation and creates a Network Files System (NFS) share. The IBM Spectrum Protect Plus agent then mounts the share on the Oracle server where the restore job is to be run. For Oracle Real Application Clusters (RAC), the restore job is run on all nodes in the cluster.

# Before you begin

Complete the following prerequisites:

• Create and run an Oracle backup job. For instructions, see "Backing up Oracle data" on page 218.

• Before an IBM Spectrum Protect Plus user can restore data, the appropriate roles and resource groups must be assigned to the user. Grant users access to resources and backup and restore operations by using the **Accounts** pane. For instructions, see Chapter 13, "Managing user access," on page 275.

Review the following restrictions:

- Point-in-time recovery is not supported if one or more data files were added to the database in the period between the chosen point in time and the time that the preceding backup job ran.
- If an Oracle database is mounted but not opened during a backup job, IBM Spectrum Protect Plus cannot determine the database **tempfile** settings that are related to **autoextensibility** and maximum size. When a database is restored from this restore point, IBM Spectrum Protect Plus cannot re-create the **tempfiles** with the original settings because they are unknown. Instead, **tempfiles** are created with default settings, "AUTOEXTEND ON" and "MAXSIZE 32767M". After the restore job is completed, you can manually update the settings.
- When restoring from a IBM Spectrum Protect archive, files will be migrated to a staging pool from the tape prior to the job beginning. Depending on the size of the restore, this process could take several hours.

#### **About this task**

The following restore modes are supported:

## **Instant access mode**

In instant access mode, no further action is taken after mounting the share. Users can complete any custom recovery by using the files in the vSnap volume.

#### Test mode

In test mode, the agent creates a new database by using the data files directly from the vSnap volume.

#### **Production mode**

In production mode, the agent first restores the files from the vSnap volume back to primary storage and then creates the new database by using the restored files.

#### **Procedure**

To define an Oracle restore job, complete the following steps:

1. In the navigation pane, click **Manage Protection** > **Applications** > **Oracle** > **Create Restore Job** to open the "Snapshot restore" wizard.

# Tips:

- You can also open the "Snapshot restore" wizard by clicking Jobs and Operations > Create Restore
   Job > Oracle.
- For a running summary of your selections in the "Snapshot restore" wizard, move the cursor to the information icon 1 in the navigation pane in the wizard.
- To bypass the optional pages in the wizard, select **Skip optional steps**.
- 2. On the **Source select** page, complete the following steps:
  - a) Click a source in the list to show the databases that are available for restore operations. You can also use the search function to search for available instances and toggle the displayed instances through the **View** filter.
  - b) Click the plus icon to the database that you want to use as the source of the restore operation. You can select more than one database from the list.
    - The selected sources are added to the restore list next to the database list. To remove an item from the list, click the minus icon next to the item.
  - c) Click **Next** to continue.

3. On the **Source snapshot** page, specify the instance of the database that you want to restore. Complete the following fields and click **Next** to continue. Some fields are not displayed until you select a related field.

Option	Description
Restore Type	Select the type of restore job:
	On-demand: Snapshot Runs a one-time restore job from a database snapshot. The restore job starts immediately upon the completion of the wizard.
	On-demand: Point in Time  Runs a one-time restore job from a point-in-time backup of a database. The restore job starts immediately upon the completion of the wizard.
	Recurring  Creates a repeating point-in-time restore job that runs on a schedule.
Restore Location Type	Select a type of location from which to restore data:  Site
	The site where snapshots were backed up. The site is defined on the <b>System</b> Configuration > Site pane.
	Cloud Offload  The cloud server where snapshots were offloaded. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Offload  The repository server where snapshots were offloaded. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
	Cloud Archive The cloud server on which snapshots were archived. The cloud server is defined on the System Configuration > Backup Storage > Cloud pane.
	Repository Archive The repository server where snapshots were archived. The repository server is defined on the System Configuration > Backup Storage > Repository Server pane.
Select a location	If you are restoring data from a site, select one of the following restore locations:
	Demo The demonstration site from which to restore snapshots.
	Primary  The primary site location from which to restore snapshots.
	Secondary  The secondary site location from which to restore snapshots.
	If you are restoring data from a cloud or repository server, select a server from the <b>Select a location</b> menu.
Date selector	For on-demand snapshot restore operations, specify a range of dates to show the available snapshots within that date range.
Restore Point	For on-demand snapshot restore operations, select a snapshot from the list of available snapshots in the selected data range.
Use alternate vSnap server for the restore job	If you are restoring data from a cloud resource or repository server, select this box to specify an alternative vSnap server, and then select a server from the <b>Select alternate vSnap</b> menu.

Option	Description	
	When you restore data from a restore point that was offloaded or archived to a cloud resource or repository server, a vSnap server is used as a gateway to complete the operation. By default, the vSnap server that is used to complete the restore operation is the same vSnap server that is used to complete the backup and offload operations. To reduce the load on the vSnap server, you can select an alternative vSnap server to serve as the gateway.	

4. On the **Set destination** page, specify where you want to restore the database and click **Next**.

# Restore to original location

Select this option to restore the database to the original server.

#### **Restore to alternate location**

Select this option to restore the database to a local destination that is different from the original server, and then select the alternative location from the list of available servers.

5. On the **Restore method** page, set the restore job to run in test, production, or instant access mode by default.

For test or production mode, you can optionally enter a new name for the restored database.

For production mode, you can also specify a new folder for the restored database by expanding the database and entering a new folder name.

Click **Next** to continue.

After the job is created, it can be run in test, production, or instant access mode in the **Job Sessions** pane.

6. On the **Job options** page, configure additional options for the restore job and click **Next** to continue.

# **Recovery Options**

Set the following point-in-time recovery options:

# Recover until end of backup

Restore the selected database to the state at the time that the backup was created.

# Recover until specific point in time

When log backup is enabled by using an Oracle Backup job definition, point-in-time restore options will be available when you create an Oracle Restore job definition. Select one of the following options, and then click **Save**:

- **By Time**. Select this option to configure a point-in-time recovery from a specific date and time.
- **By SCN**. Select this option to configure a point-in-time recovery by System Change Number (SCN).

IBM Spectrum Protect Plus finds the restore points that directly proceed and follow the selected point in time. During the recovery, the older data backup volume and the newer log backup volume are mounted. If the point in time occurred after the last backup, a temporary restore point is created.

# **Application Options**

Set the application options:

## Overwrite existing database

Enable this option to allow the restore job to overwrite the selected database. By default, this option is not selected.

# **Maximum Parallel Streams per Database**

Set the maximum number of parallel data stream from the backup storage per database. This setting applies to each database in the job definition. If the value of the option is set to 1, multiple databases can still be restored in parallel. Multiple parallel streams might improve restore speed, but high bandwidth consumption might affect overall system performance.

This option is applicable only when you are restoring an Oracle database to its original location by using its original database name.

#### **Init Params**

This option controls the initialization parameters that are used to start the recovered database in Oracle test and production workflows.

**Source**. This option is the default. IBM Spectrum Protect Plus uses the same initialization parameters as the source database, but with the following changes:

- Parameters that contain paths such as control\_files, db\_recovery\_file\_dest, or log\_archive\_dest\_\* are updated to reflect the new paths based on the renamed mount points of the recovered volumes.
- Parameters such as audit\_file\_dest and diagnostic\_dest are updated to point to the appropriate location under the Oracle base directory on the destination server if the path differs from the source server.
- If a new name is specified for the database, the **db\_name** and **db\_unique\_name** parameters are updated to reflect the new name.
- Cluster-related parameters such as instance\_number, thread, and cluster\_database
  are set automatically by IBM Spectrum Protect Plus, depending on the appropriate values for
  the destination.

**Target**. Customize the initialization parameters by specifying a template file that contains the initialization parameters that are used by IBM Spectrum Protect Plus.

The specified path must point to a plain text file that exists on the destination server and is readable by the IBM Spectrum Protect Plus user. The file must be in Oracle pfile format, consisting of lines in the following format:

```
name = value
```

Comments that begin with the # character are ignored.

IBM Spectrum Protect Plus reads the template pfile and copies the entries to the new pfile that is used to start the recovered database. However, the following parameters in the template are ignored. Instead, IBM Spectrum Protect Plus sets their values to reflect appropriate values from the source database or to reflect new paths based on the renamed mount points of the recovered volumes.

- control\_files
- db\_block\_size
- db\_create\_file\_dest
- db\_recovery\_file\_dest
- log\_archive\_dest
- spfile
- undo\_tablespace

Additionally, cluster-related parameters like **instance\_number**, **thread**, and **cluster\_database** are set automatically by IBM Spectrum Protect Plus, depending on the appropriate values for the destination.

#### **Advanced Options**

Set the advanced job definition options:

# Run cleanup immediately on job failure

Enable this option to automatically clean up allocated resources as part of a restore operation if the recovery fails.

# Allow session overwrite

Select this option to replace an existing database with a database of the same name during recovery. When an Instant Disk Restore is performed for a database and another database with

the same name is already running on the destination host or cluster, IBM Spectrum Protect Plus shuts down the existing database before starting up the recovered database. If this option is not selected, the restore job fails when IBM Spectrum Protect Plus detects a running database with the same name.

## Continue with restores of other databases even if one fails

Toggle the recovery of a resource in a series if the previous resource recovery fails. If this option is not enabled, the restore job stops if the recovery of a resource fails.

## Protocol Priority (Instant access only)

If more than one storage protocol is available, select the protocol to take priority in the job. The available protocols are **iSCSI** and **Fibre Channel**.

#### **Mount Point Prefix**

For instant access restore operations, specify the prefix for the path where the mount point is to be directed.

7. Optional: On the Apply scripts page, specify scripts that can be run before or after an operation runs at the job level. Batch and PowerShell scripts are supported on Windows operating systems, and shell scripts are supported on Linux operating systems.

#### **Pre-Script**

Select this check box to choose an uploaded script and an application or script server where the pre-script will run. To select an application server where the pre-script will run, clear the **Use** Script Server check box. Scripts and script servers are configured on the System Configuration > Script page.

# **Post-Script**

Select this check box to choose an uploaded script and an application or script server where the post-script will run. To select an application server where the post-script will run, clear the Use Script Server check box. Scripts and script servers are configured on the System Configuration > Script page.

#### Continue job/task on script error

Select this check box to continue running the job if the script that is associated with the job fails.

When you select this check box, if a pre-script or post-script completes processing with a nonzero return code, the backup or restore operation is attempted and the pre-script task status is reported as COMPLETED. If a post-script completes processing with a nonzero return code, the post-script task status is reported as COMPLETED.

If you clear this check box, the backup or restore is not attempted, and the pre-script or postscript task status is reported as FAILED.

- 8. Take one of the following actions on the **Schedule** page:
  - If you are running an on-demand job, click **Next**.
  - If you are setting up a recurring job, enter a name for the job schedule, and specify how often and when to start the restore job. Click **Next**.
- 9. On the **Review** page, review your restore job settings and click **Submit** to create the job.

#### Results

An on-demand job begins after you click **Submit**, and the **onDemandRestore** record is added to the **Job** Sessions pane shortly. To view the progress of the restore operation, expand the job. You can also

download the log file by clicking the download icon  $^{igtriangle}$  .



A recurring job will begin at the scheduled start time when you start the schedule in the **Jobs and Operations** > **Schedule** page.

All running jobs are viewable in the **Jobs and Operations** > **Running Jobs** page.

#### What to do next

Oracle databases are always restored in non-multithreaded mode. If the databases that you restored were originally in multithreaded mode, after the restore operation is completed, you must manually configure credentials and switch the databases to the multithreaded mode.

# **Related concepts**

"Configuring scripts for backup and restore operations" on page 234

Prescripts and postscripts are scripts that can be run before or after backup and restore jobs run at the job level. Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts are created locally, uploaded to your environment through the **Script** page, and then applied to job definitions.

#### **Related tasks**

"Adding an Oracle application server" on page 216

When an Oracle application server is added, an inventory of the instances and databases that are associated with the application server is captured and added to IBM Spectrum Protect Plus. This process enables you to complete backup and restore jobs, as well as run reports.

# **Chapter 9. Protecting IBM Spectrum Protect Plus**

Protect the IBM Spectrum Protect Plus application by backing up the underlying databases for disaster recovery scenarios. Configuration settings, registered resources, restore points, backup storage settings, search data, and job information are backed up to a vSnap server defined in the associated SLA policy.

# **Backing up the IBM Spectrum Protect Plus application**

Back up IBM Spectrum Protect Plus configuration settings, SLA policies, registered resources, backup storage settings, restore points, search data, and imported keys and certificates to a vSnap server that is defined in the associated SLA policy.

# Before you begin

Ensure that the appropriate SLA policy is available. To optimize backup jobs, create SLA policies specifically for backing up IBM Spectrum Protect Plus. To reduce system load, ensure other jobs are not scheduled to run during the IBM Spectrum Protect Plus backup job. To create an SLA policy, see "Creating an SLA policy" on page 87.

**Restriction:** You cannot select the onboard vSnap server as the target of the IBM Spectrum Protect Plus backup SLA policy. The onboard vSnap server is named localhost and is automatically installed when the IBM Spectrum Protect Plus appliance is initially deployed. Select a secondary external vSnap server as the target when creating an SLA policy for backup

An IBM Spectrum Protect Plus catalog can be restored to the same location, or an alternate IBM Spectrum Protect Plus location in disaster recovery scenarios.

#### **Procedure**

To back up IBM Spectrum Protect Plus data:

- 1. In the navigation pane, click Manage Protection > IBM Spectrum Protect Plus > Backup.
- Select an SLA policy to associate with the IBM Spectrum Protect Plus catalog backup operation. The SLA policy defines the scheduling of the catalog backup, along with the backup destination, replication, and offloading settings. Catalog backup data can also be offloaded to cloud resources and repository servers.
- 3. Click **Save** to create the job definition.

#### Results

The job runs as defined by the SLA policies that you selected, or you can manually run the job by clicking **Jobs and Operations** > **Schedule**. Then, select the job in the **Schedule** tab and click **Actions** > **Start**. For instructions, see "Start a backup job" on page 77.

# **Restoring the IBM Spectrum Protect Plus application**

Restore IBM Spectrum Protect Plus configuration settings, restore points, search data, and job information that were backed up to the vSnap server. The data can be restored to the same location or another IBM Spectrum Protect Plus location.

#### About this task



**Attention:** An IBM Spectrum Protect Plus restore operation overwrites all data in the IBM Spectrum Protect Plus virtual appliance or alternate virtual appliance location. All IBM Spectrum Protect Plus operations stop while the data is being restored. The user interface is not accessible, and all jobs that are running are canceled. Any snapshots that are created between the backup and restore operations are not saved.

If restoring an offloaded cloud backup, the cloud resource or repository server must be registered on the alternate IBM Spectrum Protect Plus location.

#### **Procedure**

To restore IBM Spectrum Protect Plus data:

- 1. In the navigation pane, click Manage Protection > IBM Spectrum Protect Plus > Restore.
- 2. Select a vSnap server, cloud resource, or repository server.

Data can be restored to the same location, or an alternate location in disaster recovery scenarios.

Available snapshots for the server are displayed.

- 3. Click **Restore** for the catalog snapshot that you want to restore.
- 4. Select one of the following restore modes:

## Restore the catalog and suspend all scheduled jobs

The catalog is restored and all scheduled jobs are left in a suspended state. No scheduled jobs are started, which allows for the validation and testing of catalog entries and the creation of new jobs. Typically, this option is used in DevOps use cases.

## Restore the catalog

The catalog is restored and all scheduled jobs continue to run as captured in the catalog backup. Typically, this option is used in disaster recovery.

- 5. Click Restore.
- 6. To run the restore job, in the dialog box, click Yes.

# **Managing IBM Spectrum Protect Plus restore points**

You can use the **Restore Point Retention** pane to search for restore points in the IBM Spectrum Protect Plus catalog by backup job name, view their creation and expiration dates, and override the assigned retention.

# About this task

Expiring a job session will not remove a snapshot and related recovery point if the snapshot is locked by a replication or offload relationship. Run the replication or offload-enabled job to change the lock to a later snapshot. The snapshot and recovery point will be removed during the next run of the maintenance job.

#### **Procedure**

To set a job session to expire:

- 1. In the navigation pane, click Manage Protection > IBM Spectrum Protect Plus > Restore Point Retention.
- 2. In the Backup Sessions tab, search for the desired job session or restore point. For more information about using the search function, see Appendix A, "Search guidelines," on page 293. Alternatively, in the Virtual Machines / Databases tab, select either Applications or Hypervisors to search for the desired catalog entry by entering the name. Names can be searched by entering partial text, using the asterisk (\*) as a wildcard character, or using the question mark (?) for pattern matching.
- 3. If searching from the Backup Sessions tab, use filters to fine-tune your search across job types and date range when the associated backup job started.
- 4. Click the search icon 4.
- 5. Select the job sessions you want to expire.
- 6. From the **Actions** list, select one of the following options:
  - **Expire** is used to expire a single job session.
  - Expire All Job Sessions is used to expire all unexpired job sessions for the selected job.

7. To confirm the expiration, in the dialog box, click Yes.

#### Results

The job session is removed during the next run of the maintenance job.

# **Related concepts**

"Job types" on page 231

Jobs are used to run backup, restore, maintenance, and inventory operations in IBM Spectrum Protect Plus.

# **Deleting IBM Spectrum Protect Plus resources from the catalog**

You can use the **Virtual Machines/Databases** tab in the **Restore Point Retention** pane to expire catalog metadata that is associated with a resource from the IBM Spectrum Protect Plus catalog. Resources are added to the catalog through inventory jobs. Expiring a resource removes the metadata that is associated with a restore point from the catalog, which frees up space in the catalog and removes the restore point from recovery screens.

#### **About this task**

Expiring a resource from the catalog does not remove associated snapshots from a vSnap server or secondary backup storage.

#### **Procedure**

To expire a resource from the catalog:

- 1. In the navigation pane, click Manage Protection > IBM Spectrum Protect Plus > Restore Point Retention.
- 2. Click the Virtual Machines/Databases tab.
- 3. Use the filter to search by resource type, then enter a search string to search for a resource by name. For more information about using the search function, see Appendix A, "Search guidelines," on page 293.
- 4. Click the search icon Q.
- 5. Click the delete icon X that is associated with a resource.
- 6. To confirm the expiration, in the dialog box, click Yes.

#### Results

The catalog metadata associated with the resource is removed from the catalog.

## **Related concepts**

"Job types" on page 231

Jobs are used to run backup, restore, maintenance, and inventory operations in IBM Spectrum Protect Plus.

# **Chapter 10. Jobs and operations**

Use the **Jobs and Operations** window to monitor jobs, review job history, schedule jobs, view active resources, and rerun or pause jobs and schedules.

To view and manage jobs and resources, click **Jobs and Operations** and click the appropriate tab:

- Running Jobs Shows the backup, inventory, maintenance, and restore jobs that are running.
- **Job History** Shows the jobs that failed, completed processing with warnings, or jobs that ran successfully. You can download a job log from the page by selecting the job and clicking **Download.zip**.
- Active Resources Shows application and hypervisor active resources.
- **Schedule** Shows the job schedules. You can start an on-demand job, or pause a schedule for a selected job. By using the edit icon, , you can also edit a job schedule.

You can also create on-demand or recurrent restore jobs by clicking **Create Restore Job**. For instructions about how to create restore jobs, click the links in the following table:

Table 22. Creating restore jobs	
Task	Instructions
Create restore jobs for hypervisors	See the following topics:  • "Restoring VMware data" on page 106  • "Restoring Hyper-V data" on page 121
Create restore jobs for applications	See the following topics:  • "Restoring Db2 data" on page 142  • "Restoring Exchange databases" on page 157  • "Restoring MongoDB data" on page 193  • "Restoring Oracle data" on page 220  • "Restoring SQL Server data" on page 210

# Job types

Jobs are used to run backup, restore, maintenance, and inventory operations in IBM Spectrum Protect Plus.

Backup and restore jobs are user defined. After you create these jobs, you can modify the jobs at any time. Maintenance and inventory jobs are predefined and not modifiable.

You can run all jobs on demand, even if they are set to run on a schedule. You can also hold and release jobs that are set to run on a schedule.

The following job types are available:

## Backup

A backup job defines the resources that you want to back up and the service level agreement (SLA) policy or policies that you want to apply to those resources. Each SLA policy defines when the job runs. You can run the job by using the schedule that is defined by the SLA policy or you can run the job on demand.

The job name is auto generated and is constructed of the resource type followed by the SLA policy that is used for the job. For example, a backup job for SQL Server resources that are associated with the SLA policy Gold is sql\_Gold.

#### Restore

A restore job defines the restore point that you want to restore data from. For example, if you are restoring hypervisor data, the restore point might be a virtual machine. If you are restoring application data, the restore point might be a database. You can create a schedule to run the job or you can run the job on demand.

The job name depends on whether you run the job on demand or on a schedule. If you run a restore operation on demand, the job name onDemandRestore is auto generated.

If create a job to run on a schedule, you must specify a job name.

#### **Maintenance**

The maintenance job runs once a day to remove resources and associated objects that are created by IBM Spectrum Protect Plus when a job that is in a pending state is deleted.

The cleanup procedure reclaims space on storage devices, cleans up the IBM Spectrum Protect Plus catalog, and removes related snapshots. The maintenance job also removes cataloged data that is associated with deleted jobs.

The job name is Maintenance

## **Inventory**

An inventory job is run automatically when you add a resource to IBM Spectrum Protect Plus. However, you can run an inventory job at any time to detect any changes that occurred since the resource was added.

The inventory job names are Default Application Server Inventory, Default Hypervisor Inventory, and Default Storage Server Inventory.

# **Starting jobs**

You can run any job on demand, even if the job is set to run on a schedule.

#### **Procedure**

Complete the following steps to start a job:

- 1. In the navigation pane, click **Jobs and Operations**, and click the **Schedule** tab.
- 2. Choose the job that you want to run and click **Actions** > **Start**.

The job is started and added to the **Running Jobs** tab.

# What to do next

To view the job log in detail, click the job in the **Running Jobs** tab.

The log screen shows the following details:

- Status: Shows whether the message is an error, warning, or an informational message.
- Time: Shows the time stamp of the message.
- ID: Shows the unique identifier for the message if applicable.
- · Description: Shows the message text.

You can download a job log from the page by clicking **Download.zip**. To cancel the job, click **Actions** > **Cancel**.

# Pausing and resuming jobs

You can pause and resume a scheduled job or a job that is running. When you pause a scheduled job, the job will not run until it is resumed.

#### **Procedure**

To pause and release job schedules, complete the following steps:

- 1. In the navigation pane, click **Jobs and Operations**, and click the **Schedule** tab.
- 2. Choose the job that you want to pause, and click **Actions** > **Pause Schedule**.
- 3. To resume the job schedule, click **Actions** > **Release Schedule**.

# **Canceling jobs**

You can cancel a job that is running.

#### **Procedure**

The cancel a job, complete the following steps::

- 1. In the navigation pane, click **Jobs and Operations** and then click the **Schedule** tab.
- 2. To cancel a running job session, click the **Actions** menu that is associated with the job, and then click **Cancel**.

# Rerunning partially completed backup jobs

If the last instance of a backup job was partially completed, you can rerun the job to back up virtual machines and databases that were skipped.

#### **About this task**

A backup job can be rerun only in the same session ID as the original partially completed backup job. No successful backup of the same resource can have completed since the partial backup job you choose to rerun.

**Note:** Backup jobs can be rerun only in response to a hypervisor or database backup failure. The following events do not qualify for backup job rerun operations:

- A VM backup was completed with an FLI failure.
- A snapshot condense failure occurred for a storage system.
- A backup job failed with an unknown issue such as a cataloging error.
- A resource is missing from the vCenter.

For applications for which log backups are supported, log backups are not disabled when using the rerun feature. Log backups will be disabled for the applicable databases when the job is next started without using the on-demand backup or rerun feature.

#### **Procedure**

Complete the following steps to rerun a partially completed backup operation:

- 1. In the navigation pane, click **Jobs and Operations** and then click the **Job History** tab.
- 2. Use the search function and filters to find the last instance of the backup job that was partially completed.
- 3. Select the job instance, then click **Rerun**.

#### Note:

If the backup job cannot be rerun, the **Rerun** option is not available.

All SLA options and any exclusions that are associated with the original job are included in the rerun operation. No option or exclusion changes are applied since the partial backup completed. If the rerun job is completed successfully, the job summary is updated to show success.

# **Backing up a single resource**

If a hypervisor or application server is associated with an SLA policy, a single virtual machine or application can be backed up immediately by running an on-demand backup operation. Select **Run** in a hypervisor or application server backup screen to run an on-demand backup operation. This option is enabled when an existing SLA policy is associated with the resource.

#### About this task

Rerunning a backup job for a single resource is applicable only for backup operations, not replication or offload operations.

For applications for which log backups are supported, log backups are not disabled when using the ondemand backup or rerun feature. Log backups will be disabled for the applicable databases when the job is next started without using the on-demand backup or rerun feature.

#### **Procedure**

Complete the following steps to run an on-demand backup job of a single virtual machine or application server:

- 1. In the navigation pane, click **Manage Protection**. Depending on the type of backup operation, select **Hypervisors** > **Backup**, or **Applications** > **Backup**.
- 2. Click one of the listed instances to show the associated virtual machine or application resources. The hypervisor or application server must be associated with an existing SLA policy.
- 3. Click Run.
  - If the virtual machine or application is a member of multiple SLA policies, select the SLA policy to run for the on-demand job.
- 4. To confirm the backup job, in the dialog box, click **OK**.

# Configuring scripts for backup and restore operations

Prescripts and postscripts are scripts that can be run before or after backup and restore jobs run at the job level. Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts are created locally, uploaded to your environment through the **Script** page, and then applied to job definitions.

#### Before you begin

Review the following considerations for using scripts with hypervisors:

- The user who is running the script must have the **Log on as a service** right enabled, which is required for running prescripts and postscripts. For more information about this right, see Add the Log on as a service Right to an Account.
- Windows Remote Shell (WinRM) must be enabled.

# **Uploading a script**

Supported scripts include shell scripts for Linux-based machines and Batch and PowerShell scripts for Windows-based machines. Scripts must be created using the associated file format for the operating system.

#### **Procedure**

Complete the following steps to upload a script:

- 1. In the navigation pane, click **System Configuration** > **Script**.
- 2. In the Scripts section, click Upload Script.

The **Upload Script** pane displays.

- 3. Click **Browse** to select a local script to upload.
- 4. Click Save.

The script displays in the **Scripts** table and can be applied to supported jobs.

#### What to do next

After you upload the script, complete the following action:

Action	How to
Add the script to a server from which it will run.	See "Adding a script to a server" on page 235.

# Adding a script to a server

Add the script to a server from which it will run.

#### **Procedure**

Complete the following steps to designate a script to a server:

- 1. In the navigation pane, click **System Configuration** > **Script**.
- 2. In the Script Servers section, click Add Script Server.

The Script Server Properties pane displays.

3. Set the server options.

#### **Host Address**

Enter the resolvable IP address or a resolvable path and machine name.

# Use existing user

Enable to select a previously entered user name and password for the provider.

#### Username

Enter your username for the provider. If entering a SQL server, the user identity follows the default domain\name format if the virtual machine is attached to a domain. The format local\_administrator is used if the user is a local administrator.

#### **Password**

Enter your password for the provider.

# **OS Type**

Select the operating system of the application server.

4. Click Save.

# Chapter 11. Configuring and maintaining the IBM Spectrum Protect Plus system environment

System management tasks include adding backup storage, managing sites, registering Lightweight Directory Access Protocol (LDAP) or Simple Mail Transfer Protocol (SMTP) servers, and managing keys and certificates for cloud resources.

Maintenance tasks include reviewing the configuration of the IBM Spectrum Protect Plus virtual appliance, collecting log files for troubleshooting, and managing Secure Sockets Layer (SSL) certificates.

In most cases, IBM Spectrum Protect Plus is installed on a virtual appliance. The virtual appliance contains the application and the inventory. Maintenance tasks are completed in vSphere Client, by using the IBM Spectrum Protect Plus command line, or in a web-based management console.

Maintenance tasks are completed by a system administrator. A system administrator is usually a senior-level user who designed or implemented the vSphere and ESX infrastructure, or a user with an understanding of IBM Spectrum Protect Plus, VMware, and Linux command-line usage.

Infrastructure updates are managed by IBM update facilities. The administrative console serves as the primary means for updating IBM Spectrum Protect Plus features and underlying infrastructure components, including the operating system and file system.



**Attention:** Update underlying components of IBM Spectrum Protect Plus only by using the update facilities that are provided by IBM.

# Managing secondary backup storage

The vSnap server is the primary backup location for snapshots. All IBM Spectrum Protect Plus environments have at least one vSnap server. Optionally, you can offload snapshots from a vSnap server to a cloud storage system or a repository server.

For information about offloading snapshot data to secondary storage, see <u>"Offload to secondary backup</u> storage" on page 6.

# Managing cloud storage

You can oflload to cloud storage for longer-term data protection.

#### Adding Amazon S3 cloud storage as a backup storage provider

Add Amazon S3 cloud storage to enable IBM Spectrum Protect Plus to offload data to S3.

#### Before you begin

Configure the key that is required for the cloud object. For instructions, see <u>"Adding an access key" on page 245.</u>

Ensure that there are cloud storage buckets created for the IBM Spectrum Protect Plus data before you add the cloud storage in the following steps. For information how to create buckets, see <u>Amazon Simple Storage Service Documentation</u>.

## **Procedure**

To add Amazon S3 cloud storage as backup storage provider, complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Cloud.
- 2. Click Add Cloud.
- 3. From the **Provider** list, select **Amazon S3**.
- 4. Complete the fields in the **Cloud Registration** pane:

#### Name

Enter a meaningful name to help identify the cloud storage.

## Region

Select the Amazon Web Services (AWS) regional endpoint of the cloud storage.

# Use existing key

Enable to select a previously entered key for the storage, and then select the key from the **Select a key** list.

If you do not select this option, complete the following fields to add a key:

## **Key name**

Enter a meaningful name to help to identify the key.

## **Access key**

Enter the AWS access key. Access keys are created through the AWS Management Console.

# Secret key

Enter the AWS secret key. Secret keys are created through the AWS Management Console.

5. Click **Get Buckets**, and then select a bucket to serve as the offload target.

After the buckets are generated, the **Offload bucket** and **Archive bucket** fields are displayed.

- 6. In the **Offload bucket** field, select a bucket to serve as the offload target.
- 7. Optional: In the **Archive bucket** field, select a cloud storage resource to serve as the archive target. Archiving data creates a full data copy and can provide longer-term protection, cost, and security benefits. For more information about archiving data, see the information about copying data to cloud archive storage in "Offload to secondary backup storage" on page 6.
- 8. Click Register.

The cloud storage is added to the cloud servers table.

#### What to do next

After you add the S3 storage, complete the following action:

Action	How to
Associate the cloud storage with the SLA policy that is used for the backup job.	To create an SLA policy, see <u>"Creating an SLA policy"</u> on page 87.
	To modify an existing SLA policy, see <u>"Editing an SLA policy" on page 91</u> .

#### Adding IBM Cloud Object Storage as a backup storage provider

Add IBM Cloud Object Storage to enable IBM Spectrum Protect Plus to offload data to IBM Cloud.

#### Before you begin

Configure the key and certificate that are required for the cloud object. For instructions, see <u>"Adding an</u> access key" on page 245 and "Adding a certificate" on page 246.

Ensure that there are cloud storage buckets created for the IBM Spectrum Protect Plus data before you add the cloud storage in the following steps. For information how to create buckets, see <u>About IBM Cloud</u> Object Storage.

When creating a bucket on IBM Cloud Object Storage (COS), ensure that both **Add Archive rule** and **Add Experation rules** are not selected when creating buckets that are to be used for copy or archive. This can result in a failure with the "bucket has an unsupported lifecycle configuration" error when the job attempts to run in IBM Spectrum Protect Plus. The **Add Retention policy** option may be set for a bucket to be used for copy, but should not be set for a bucket that will be used for archiving.

The Cold Vault bucket of type should only be used when archiving, as it is the lowest-cost option and is described as ideal for long-term retention of data that will be minimally accessed.

When adding IBM Cloud Object Storage (COS), the method for obtaining the access and secret key will depend on the deployment model. If on-premise, keys can be obtained from the IBM COS Manager Console. For IBM COS IaaS, keys are created when a service account is created and can be obtained from the softlayer portal. If using IBM COS (COS as a Service), the access and secret key are not created by default; when a service account is created, check the **Include HMAC Credential** box, and add {"HMAC":true} to the **Add Inline Configuration Parameters** text area.

#### **Procedure**

To add IBM Cloud Object Storage as a backup storage provider, complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Cloud.
- 2. Click Add Cloud.
- 3. From the **Provider** list, select **IBM Cloud Object Storage**.
- 4. Complete the fields in the **Cloud Registration** pane:

#### Name

Enter a meaningful name to help identify the cloud storage.

# **Endpoint**

Select the endpoint of the cloud storage.

## Use existing key

Enable to select a previously entered key for the storage, and then select the key from the **Select a key** list.

If you do not select this option, complete the following fields to add a key:

## Key name

Enter a meaningful name to help to identify the key.

## Access key

Enter the access key.

## Secret key

Enter the secret key.

# Certificate

Select a method of associating a certificate with the resource:

#### Upload

Select and click **Browse** to locate the certificate, then click **Upload**.

#### Copy and paste

Select to enter the name of the certificate, copy and paste the contents of the certificate, then click **Create**.

#### Use existing

Select to use a previously uploaded certificate.

A certificate is not required if you are adding public IBM Cloud Object Storage.

5. Click **Get Buckets**, and then select a bucket to serve as the offload target.

After the buckets are generated, the **Offload bucket** and **Archive bucket** fields are displayed.

- 6. In the **Offload bucket** field, select a bucket to serve as the offload target.
- 7. Optional: In the **Archive bucket** field, select a cloud storage resource to serve as the archive target. Archiving data creates a full data copy and can provide longer-term protection, cost, and security benefits. For more information about archiving data, see the information about copying data to cloud archive storage in "Offload to secondary backup storage" on page 6.
- 8. Click **Register**.

ı

The cloud storage is added to the cloud servers table.

#### What to do next

After you add the IBM Cloud Object Storage, complete the following action:

Action	How to
Associate the cloud storage with the SLA policy that is used for the backup job.	To create an SLA policy, see "Creating an SLA policy" on page 87.
	To modify an existing SLA policy, see <u>"Editing an SLA policy"</u> on page 91.

# Adding Microsoft Azure cloud storage as a backup storage provider

Add Microsoft Azure cloud storage to enable IBM Spectrum Protect Plus to offload data to Microsoft Azure Blob storage.

# Before you begin

Ensure that there are cloud storage buckets created for the IBM Spectrum Protect Plus data before you add the cloud storage in the following steps. For information how to create buckets, see Azure documentation.

#### **Procedure**

To add Microsoft Azure cloud storage as backup storage provider, complete the following steps:

- 1. In the navigation pane, click System Configuration > Backup Storage > Cloud.
- 2. Click Add Cloud.
- 3. From the Provider list, select Microsoft Azure Blob Storage.
- 4. Complete the fields in the Cloud Registration pane:

#### Name

Enter a meaningful name to help identify the cloud storage.

## **Endpoint**

Select the endpoint of the cloud storage.

#### Use existing key

Enable to select a previously entered key for the storage, and then select the key from the **Select a key** list.

If you do not select this option, complete the following fields to add a key:

#### Key name

Enter a meaningful name to help identify the key.

#### **Storage Account Name**

Enter the Microsoft Azure access storage account name. This is from the Azure Management Portal.

#### **Storage Account Shared Key**

Enter the Microsoft Azure key from any one of the key fields in the Azure Management Portal, either key1 or key2.

5. Click **Get Buckets**, and then select a bucket to serve as the offload target.

After the buckets are generated, the **Offload bucket** and **Archive bucket** fields are displayed.

- 6. In the **Offload bucket** field, select a bucket to serve as the offload target.
- 7. Optional: In the **Archive bucket** field, select a cloud storage resource to serve as the archive target. Archiving data creates a full data copy and can provide longer-term protection, cost, and security benefits. For more information about archiving data, see the information about copying data to cloud archive storage in "Offload to secondary backup storage" on page 6.
- 8. Click Register.

The cloud storage is added to the cloud servers table.

#### What to do next

After you add the Microsoft Azure storage, complete the following action:

Action	How to
Associate the cloud storage with the SLA policy that is used for the backup job.	To create an SLA policy, see "Creating an SLA policy" on page 87.
	To modify an existing SLA policy, see <u>"Editing an SLA policy" on page 91</u> .

### Adding S3 compatible cloud storage

Before you can back up data to Simple Storage Service (S3) compatible cloud storage, you must complete configuration tasks.

### Before you begin

Configure the key that is required for the cloud object. For instructions, see <u>"Adding an access key" on page 245.</u>

Ensure that cloud storage buckets are available. For more information about cloud storage buckets, see the documentation for the S3 compatible storage provider.

**Restriction:** The cloud S3 compatible option is available only if you install IBM Spectrum Protect Plus interim fix 10.1.4.222 or later.

#### **Procedure**

To add S3 compatible cloud storage as a backup target, complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Cloud.
- 2. Click Add Cloud.
- 3. From the **Provider** list, select **S3 Compatible Storage**.
- 4. Complete the fields in the Cloud Registration pane:

#### Name

Enter a meaningful name to help identify the cloud storage.

#### **Endpoint**

Enter the endpoint of the cloud storage.

### Use existing access key

Enable this option to select a previously entered key for the storage, and then select the key from the **Select a key** list.

If you do not select this option, complete the following fields to add a key:

#### **Key name**

Enter a meaningful name to identify the key.

#### **Access key**

Enter the S3 compatible access key. For instructions about obtaining access keys, see the documentation for the S3 compatible storage provider.

### **Secret key**

Enter the S3 compatible secret key. For instructions about obtaining access keys, see the documentation for the S3 compatible storage provider.

### Certificate

Select the appropriate option to add a certificate for the S3 compatible storage:

#### Upload

To upload a certificate, click the **Browse** button, locate and select the certificate, and click the **Upload** button.

#### Copy and paste

Enter a name for the certificate and paste the certificate into the text area. Click the **Create** button.

### **Use existing**

If a certificate exists, select the certificate from the **Select a certificate** list.

- 5. Click **Get Buckets**, and then select a bucket to serve as the target.
  - After the buckets are generated, the Offload bucket and Archive bucket fields are displayed.
- 6. In the **Offload bucket** field, select a bucket to serve as the backup target.
- 7. Optional: In the **Archive bucket** field, select a cloud storage resource to serve as the archive target. Archiving data creates a full data copy and can provide longer-term protection, cost, and security benefits. For more information about archiving data, see the information about copying data to cloud archive storage in "Offload to secondary backup storage" on page 6.
- 8. Click Register.

The cloud storage is added to the cloud servers table.

#### What to do next

After you add the S3 compatible storage, complete the following action:

Action	How to
Associate the cloud storage with the SLA policy that is used for the backup job.	To create an SLA policy, see <u>"Creating an SLA policy"</u> on page 87.
	To modify an existing SLA policy, see <u>"Editing an SLA policy" on page 91</u> .

### **Editing settings for cloud storage**

Edit the settings for a cloud storage provider to reflect changes in your cloud environment.

#### **Procedure**

To edit a cloud storage provider, complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Cloud.
- 2. Click the edit icon / that is associated with a cloud provider.
  - The **Update Cloud** pane is displayed.
- 3. Revise the settings for the cloud provider, and then click **Update**.

### **Deleting cloud storage**

Delete a cloud storage provider to reflect changes in your cloud environment. Ensure that the provider is not associated with any SLA policies before deleting the provider.

### **Procedure**

To delete a cloud storage provider, complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Cloud.
- 2. Click the delete icon  $\times$  that is associated with a provider.
- 3. Click **Yes** to delete the provider.

### Managing repository server storage

You can offload to a repository server for longer-term data protection. For the current release of IBM Spectrum Protect Plus, the repository server must be an IBM Spectrum Protect server Version 8.1.7 or later.

### **Configuring an IBM Spectrum Protect server as an offload target**

To offload data to an IBM Spectrum Protect server, you must first set up IBM Spectrum Protect Plus as an object client to the server.

#### About this task

After you set up an object client, keys and a certificate are provided to enable a secure connection to the IBM Spectrum Protect server. These items are required to add the repository server in IBM Spectrum Protect Plus.

To add the object client, you must be familiar with the IBM Spectrum Protect server environment and have experience working with the Operations Center or with IBM Spectrum Protect server administrative commands. For assistance, contact your IBM Spectrum Protect administrator.

IBM Spectrum Protect Plus is aware of offloads to the IBM Spectrum Protect server, but is not aware of subsequent IBM Spectrum Protect server replication operations.

Documentation about configuring IBM Spectrum Protect as an offload target is available in IBM Knowledge Center as follows:

- For an overview of the configuration process, see Offloading data from IBM Spectrum Protect Plus
- For prerequisites for the offload process, see Preparing to offload data from IBM Spectrum Protect Plus
- For AIX operating system information, see Configuring to offload data in AIX® environments
- For Linux or Windows operating systems information, see <u>Configuring to offload data in Linux and</u> Windows environments

#### **Related tasks**

"Adding a repository server as a backup storage provider" on page 243
Add a repository server to enable IBM Spectrum Protect Plus to offload data to the server.

### Adding a repository server as a backup storage provider

Add a repository server to enable IBM Spectrum Protect Plus to offload data to the server.

### Before you begin

Configure the key and certificate that are required for the repository server. For instructions, see <u>"Adding"</u> an access key" on page 245 and "Adding a certificate" on page 246.

For the current release of IBM Spectrum Protect Plus, the repository server must be an IBM Spectrum Protect server.

Configure IBM Spectrum Protect Plus as an object client to the IBM Spectrum Protect server. The object client node transfers and stores offloaded data. After you complete the setup procedure, the wizard provides you with the endpoint for communicating with the object agent on the server, and the access ID, secret key, and certificate for connecting securely. "Configuring an IBM Spectrum Protect server as an offload target" on page 243.

Certificates can be obtained from the IBM Spectrum Protect server Operations Center by navigating to the following pane: **Server** > **Object Agent** > **Agent Certificate**. Alternatively, the certificate can be obtained from the IBM Spectrum Protect Plus appliance by running the following command: openssl s\_client -showcerts -connect <ip-address>:9000 </dev/null 2>/dev/null | openssl x509

Offload retention settings are fully controlled through associated SLA policies in IBM Spectrum Protect Plus. IBM Spectrum Protect server copygroup retention settings are not used for offload operations.

#### **Procedure**

To add an IBM Spectrum Protect server as backup storage provider complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Repository Server.
- 2. Click Add Repository Server.
- 3. Complete the fields in the Register Repository Server pane:

#### Name

Enter a meaningful name to help identify the repository server.

#### Hostname

Enter the high-level address (HLA) of the repository server object agent. Running the IBM Spectrum Protect q serv OBJAGENT f=d command retrieves this information.

#### **Port**

Enter the communications port of the repository server.

### Use existing key

Enable to select a previously entered key for the repository, and then select the key from the **Select a key** list.

If you do not select this option, complete the following fields to add a key:

#### **Key name**

Enter a meaningful name to help to identify the key.

#### Access key

Enter the access key.

### Secret key

Enter the secret key.

#### Certificate

Select a method of associating a certificate with the resource. If copying the certificate, the BEGIN and END lines of text must be included.

#### Upload

Select and click **Browse** to locate the certificate, then click **Upload**.

#### Copy and paste

Select to enter the name of the certificate, copy and paste the contents of the certificate, then click **Create**.

#### Use existing

Select to use a previously uploaded certificate.

#### 4. Click **Register**.

The IBM Spectrum Protect server is added to the repository servers table.

#### What to do next

After you add a repository server, complete the following action:

Action	How to
Associate the repository server with the SLA policy that is used for the backup job.	To create an SLA policy, see "Creating an SLA policy" on page 87.
	To modify an existing SLA policy, see <u>"Editing an SLA policy"</u> on page 91.

### Editing settings for a repository server

Edit the settings for a repository server provider to reflect changes in your cloud environment.

#### **Procedure**

To edit a repository server provider, complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Repository Server.
- 2. Click the edit icon  ${\color{red} {f /}}$  that is associated with a repository server provider.
  - The **Update Repository Server** pane is displayed.
- 3. Revise the settings for the repository server provider, and then click **Update**.

### Deleting a repository server

Delete a repository server provider to reflect changes in your environment. Ensure that the provider is not associated with any SLA policies before deleting the provider.

#### **Procedure**

To delete a repository server provider, complete the following steps:

- 1. In the navigation menu, click System Configuration > Backup Storage > Repository Server.
- 2. Click the delete icon X that is associated with a repository server provider.
- 3. Click Yes to delete the provider.

### Managing keys and certificates

Cloud resources and repository servers require credentials to serve as offloading destinations. Access keys and secret keys are provided by your cloud resource or repository server interface. These keys serve as the user name and password of your offload destinations and allow them to be accessed by IBM Spectrum Protect Plus. Some offload destinations also require certificates for additional data security.

When utilizing a resource in IBM Spectrum Protect Plus that requires credentials to access an offloading destination, select **Use existing key** or **Use existing certificate**, and select the associated key or certificate.

### Adding an access key

Add an access key to provide cloud resource or repository server credentials.

#### **Procedure**

To add a key, complete the following steps:

- 1. Create your access key and secret key through the interface of the cloud resource or repository server. Make note of the access key and secret key.
- 2. In the navigation menu, click System Configuration > Keys and Certificates.
- 3. From the Access Keys section, click Add Access Key.
- 4. Complete the fields in the **Key Properties** pane:

#### Name

Enter a meaningful name to help identify the access key.

#### **Access Key**

Enter the access key of the cloud resource or repository server. For Microsoft Azure, enter the storage account name.

### Secret Key

Enter the secret key of the cloud resource or repository server. For Microsoft Azure, enter the key from one of the key fields, either key1 or key2.

5. Click Save.

The key displays in the **Access Keys** table and can be selected when utilizing a feature that requires credentials to access a resource through the **Use existing key** option.

### Deleting an access key

Delete an access key when it becomes obsolete. Ensure that you reassign a new access key to your cloud resource or repository server.

#### **Procedure**

To delete an access key, complete the following steps:

- 1. In the navigation menu, click System Configuration > Keys and Certificates.
- 2. Click the delete icon  $\times$  that is associated with an access key.
- 3. Click Yes to delete the access key.

### Adding a certificate

Add a certificate to provide cloud resource or repository server credentials.

#### **Procedure**

To add a certificate, complete the following steps:

- 1. Export a certificate from your cloud resource or repository server.
- 2. In the navigation menu, click **System Configuration** > **Keys and Certificates**.
- 3. In the Certificates section, click Add Certificate.
- 4. Complete the fields in the **Certificate Properties** pane:

### Type

Select the cloud resource or repository server type.

#### Certificate

Select a method to add the certificate:

#### Upload

Select to browse for the certificate locally.

### **Copy and paste**

Select to enter the name of the certificate and copy and paste the contents of the certificate.

5. Click Save.

The key displays in the **Certificates** table and can be selected when utilizing a feature that requires credentials to access a resource through the **Use existing certificate** option.

#### **Deleting a certificate**

Delete a certificate when it becomes obsolete. Ensure that you reassign a new certificate to your cloud resource or repository server.

#### **Procedure**

To delete a certificate, complete the following steps:

- 1. In the navigation menu, click System Configuration > Keys and Certificates.
- 2. Click the delete icon X that is associated with a certificate.
- 3. Click Yes to delete the certificate.

#### Adding an SSH key

You can add an SSH key to provide credentials for Linux-based resources on virtual machines managed by vCenter and Hyper-V, as well as Oracle, Db2, and MongoDB application servers. SSH keys help to provide

a secure connection between IBM Spectrum Protect Plus and target resources for file indexing and restore operations.

### Before you begin

- The SSH service must be running on port 22 on the server and any firewalls must be configured to allow IBM Spectrum Protect Plus to connect to the server using SSH. The SFTP subsystem for SSH must also be enabled.
- The user account on the target resource that is used to generate the SSH key pair must have **sudo** privileges. This account, which will be assigned to IBM Spectrum Protect Plus, is known as the IBM Spectrum Protect Plus user agent (sppagent).
- If the environment includes virtual machines managed by vCenter, ensure that the latest VMware Tools are installed.

#### **Procedure**

To add a key, complete the following steps:

1. On the target resource, generate an SSH key by using the ssh-keygen command with the user account that will be assigned to IBM Spectrum Protect Plus. This account must have **sudo** privileges. For example, on an Oracle server, enter the following command in the terminal and follow the instructions:

```
ssh-keygen
```

If you use the default settings, two files are created in the specified directory: id\_rsa.pub is the public key and id\_rsa is the private key.

2. When prompted enter the file name in which the key will be saved, enter a directory and file name. If you do not specify a directory and file name, the default is used:

```
/home/priveleged_user/.ssh/id_rsa
```

where *priveleged\_user* is the account assigned to IBM Spectrum Protect Plus, sppagent. If a key with the default name already exists, this will be indicated with the message displayed below. Be careful not to overwrite preexisting keys if they are in use. Press **N** to enter a different file in which to save the key.

```
/home/<priveleged user>/.ssh/id_rsa already exists. Overwrite (y/n)?
```

This procedure is based on the assumption that the key is saved in the default location using the default file name (id\_rsa). If the key file is created using a different file name, use that file name in the steps that follow.

- 3. Supply a passphrase and press Enter. Otherwise, simply press Enter for no passphrase.
- 4. If a passphrase was supplied, enter it again. Press Enter.
- 5. Copy the contents of the id\_rsa.pub key into the authorized\_keys file. If the file already exists, append the public key to the authorized\_keys file.

```
cat ~/.ssh/id_rsa.pub >> ~/.ssh/authorized_keys
```

6. Assign the required privileges to the authorized\_keys file by issuing the chmod 600 command.

```
chmod 600 ~/.ssh/authorized_keys
```

7. Edit the /etc/ssh/sshd\_config file to set the PubkeyAuthentication setting to yes by using a text editor. To ensure that the setting is not commented out, remove the number sign (#) if it appears at the beginning of the line.

```
sudo vi /etc/ssh/sshd_config
```

```
...
PubkeyAuthentication yes
...
```

8. Restart the SSH service on the target resource.

```
systemctl restart sshd
```

- 9. In the IBM Spectrum Protect Plus navigation pane, click **System Configuration** > **Keys and Certificates**.
- 10. From the SSH Keys section, click Add SSH Key.
- 11. Complete the fields in the **SSH Key Properties** pane:

#### Name

Enter a meaningful name to identify the SSH key.

#### User

Enter the user account that is associated with the target resource and SSH key. This is the user account used to generate the public and private keys in the previous steps.

#### **Encrypted**

Check this box if a passphrase was supplied when generating the public and private key.

#### **Passphrase**

This box is only displayed if the **Encrypted** check box is selected. If a passphrase was supplied when generating the public and private key, provide the passphrase in this box.

#### **Private key**

Copy and paste the private key into this box. This will be the key contained in the id\_rsa file on the target resource. The file is similar to the following example:

```
cat ~/.ssh/id_rsa

----BEGIN OPENSSH PRIVATE KEY----
ZRYtuinjaHx2mKgW4LnfqzlyAIIq5Amasi/J8/AAAFiFiP4GZYj+BmAAAAB3NzaC1yc2
...
Q5ZqZ1Ec8N7dsAAAANdG9vckBVYnVudHVWQgECAwQFBg==
----END OPENSSH PRIVATE KEY-----
```

#### 12. Click Save.

The key is displayed in the **SSH Keys** table and can be selected when you use a feature that requires credentials to access a resource with the **Key** option.

#### Deleting an SSH key

Delete an SSH key when it becomes obsolete. Ensure that you reassign a new SSH key to your resources.

#### **Procedure**

To delete an SSH key, complete the following steps:

- 1. In the navigation menu, click System Configuration > Keys and Certificates.
- 2. Click the delete icon  $\times$  that is associated with an SSH key.
- 3. Click Yes to delete the access key.

# **Managing sites**

A site is an IBM Spectrum Protect Plus policy construct that is used to manage the placement of data in an environment.

A site can be physical, such as a data center, or logical, such as a department or organization. IBM Spectrum Protect Plus components are assigned to sites to localize and optimize data paths. An IBM Spectrum Protect Plus deployment always has at least one site per physical location.

By default, the IBM Spectrum Protect Plus environment has a primary site, a secondary site, and a demo site.

### Adding a site

After you add a site to IBM Spectrum Protect Plus, you can assign backup storage servers to the site.

#### **Procedure**

To add a site, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Site**.
- 2. Click Add Site.

The **Site Properties** pane is displayed.

- 3. Enter a site name.
- 4. Optional: To manage the network activity on a defined schedule, change the throughput for site replication and offload operations:
  - a) Select the **Enable Throttle** check box.
  - b) In the **Rate** field, adjust the throughput:
    - 1) Change the numerical rate of throughput by clicking the up or down arrows.
    - 2) Select a unit for the throughput. The choices include bytes/s, KB/s, MB/s, and GB/s.

The default throughput is 100 MB/s (megabytes per second).




Figure 29. Enabling different rates of throttling for different times to improve throughput

c) In the weekly schedule table, select daily times for throttling, or select specific days and times for throttling.

**Tip:** To select a time, click a timeslot in the table. The selected timeslot is highlighted. To clear a timeslot, click a highlighted time slot. To select the same timeslot for every day of the week, click a timeslot in the **All** row.

After you make your selections, throttling days and times are listed underneath the schedule table.

5. Click **Save** to commit the changes and close the pane.

#### Results

The site is displayed in the sites table and can be applied to new and existing backup storage servers.

### **Editing a site**

Revise site information to reflect changes in your IBM Spectrum Protect Plus environment.

#### **Procedure**

To edit a site, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Site**.
- 2. Click the edit icon / that is associated with a site.

The Site Properties pane is displayed.

- 3. Revise the site name.
- 4. Optional: To manage the network activity on a defined schedule, change the throughput for site replication and offload operations:
  - a) Select the Enable Throttle check box.
  - b) In the **Rate** field, adjust the throughput:
    - 1) Change the numerical rate of throughput by clicking the up or down arrows.

2) Select a unit for the throughput. The choices include **bytes/s**, **KB/s**, **MB/s**, and **GB/s**. The default throughput is 100 MB/s (megabytes per second).




Figure 30. Enabling different rates of throttling for different times to improve throughput

c) In the weekly schedule table, select daily times for throttling, or select specific days and times for throttling.

**Tip:** To select a time, click a timeslot in the table. The selected timeslot is highlighted. To clear a timeslot, click a highlighted time slot. To select the same timeslot for every day of the week, click a timeslot in the **All** row.

After you make your selections, throttling days and times are listed underneath the schedule table.

5. Click **Save** to commit the changes and close the pane.

### **Deleting a site**

Delete a site when it becomes obsolete. Ensure that you reassign your backup storage to different sites before deleting the site.

#### **Procedure**

To delete a site, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **Site**.
- 2. Click the delete icon X that is associated with a site.
- 3. Click Yes to delete the site.

# **Managing LDAP and SMTP servers**

You can add a Lightweight Directory Access Protocol (LDAP) and Simple Mail Transfer Protocol (SMTP) server for use in the IBM Spectrum Protect Plus for use in user account and report features.

### **Related tasks**

"Creating a user account for an LDAP group" on page 283

Add a user account for an LDAP group to IBM Spectrum Protect Plus.

### "Scheduling a report" on page 272

You can schedule customized reports in IBM Spectrum Protect Plus to run at specific times.

### Adding an LDAP server

You must add an LDAP server to create IBM Spectrum Protect Plus user accounts by using an LDAP group. These accounts allows users to access IBM Spectrum Protect Plus by using LDAP user names and passwords. Only one LDAP server can be associated with an instance of IBM Spectrum Protect Plus virtual appliance.

#### **About this task**

You can add a Microsoft Active Directory or OpenLDAP server. Note that OpenLDAP does not support the sAMAaccountName user filter that is commonly used with Active Directory. Additionally, the **memberOf** option must be enabled on the OpenLDAP server.

#### **Procedure**

To register an LDAP server, complete the following steps:

- 1. In the navigation pane, click **System Configuration** > **LDAP/SMTP**.
- 2. In the LDAP Servers pane, click Add LDAP Server.
- 3. Populate the following fields in the **LDAP Servers** pane:

#### **Host Address**

The IP address of the host or logical name of the LDAP server.

#### **Port**

The port on which the LDAP server is listening. The typical default port is 389 for non SSL connections or 636 for SSL connections.

### SSL

Enable the SSL option to establish a secure connection to the LDAP server.

### Use existing user

Enable to select a previously entered user name and password for the LDAP server.

### **Bind Name**

The bind distinguished name that is used for authenticating the connection to the LDAP server. IBM Spectrum Protect Plus supports simple bind.

#### **Password**

The password that is associated with the Bind Distinguished Name.

#### **Base DN**

The location where users and groups can be found.

### **User Filter**

A filter to select only those users in the Base DN that match certain criteria. An example of a valid default user filter is  $cn=\{0\}$ .

### Tips:

- To enable authentication by using the **sAMAccountName** Windows user naming attribute, set the filter to samaccountname={0}. When this filter is set, users log in to IBM Spectrum Protect Plus by using only a user name. A domain is not included.
- To enable authentication using the user principal name (UPN) naming attribute, set the filter to userprincipalname={0}. When this filter is set, users log in to IBM Spectrum Protect Plus by using the username@domain format.

• To enable authentication by using an email address that is associated with LDAP, set the filter to mail={0}.

The **User Filter** setting also controls the type of user name that appears in the IBM Spectrum Protect Plus display of users.

#### **User RDN**

The relative distinguished path for the user. Specify the path where user records can be found. An example of a valid default RDN is cn=Users.

#### **Group RDN**

The relative distinguished path for the group. If the group is at a different level than the user path, specify the path where group records can be found.

4. Click Save.

#### Results

IBM Spectrum Protect Plus completes the following actions:

- 1. Confirms that a network connection is made.
- 2. Adds the LDAP server to the database.

After the SMTP server is added, the **Add LDAP Server** button is no longer available.

#### What to do next

If a message is returned indicating that the connection is unsuccessful, review your entries. If your entries are correct and the connection is unsuccessful, contact a network administrator to review the connections.

#### **Related tasks**

"Creating a user account for an LDAP group" on page 283

Add a user account for an LDAP group to IBM Spectrum Protect Plus.

### Adding an SMTP server

You must add an SMTP server to send scheduled reports to email recipients. Only one SMTP server can be associated with a IBM Spectrum Protect Plus virtual appliance.

#### **Procedure**

To add an SMTP server, complete the following steps:

- 1. In the navigation pane, click System Configuration > LDAP/SMTP.
- 2. In the SMTP Servers pane, click Add SMTP Server.
- 3. Populate the following fields in the **SMTP Servers** pane:

#### **Host Address**

The IP address of the host, or the path and host name of the SMTP server.

#### **Port**

The communications port of the server that you are adding. The typical default port is 25 for non-SSL connections or 443 for SSL connections.

#### Username

The name that is used to access the SMTP server.

#### **Password**

The password that is associated with the user name.

#### **Timeout**

The email timeout value in milliseconds.

#### **From Address**

The address that is associated with email communications from IBM Spectrum Protect Plus.

#### **Subject Prefix**

The prefix to add to the email subject lines sent from IBM Spectrum Protect Plus.

4. Click Save.

#### **Results**

IBM Spectrum Protect Plus completes the following actions:

- 1. Confirms that a network connection is made.
- 2. Adds the server to the database.

If a message is returned indicating that the connection is unsuccessful, review your entries. If your entries are correct and the connection is unsuccessful, contact a network administrator to review the connections.

To test the SMTP connection, click the **Test SMTP Server** button, then enter an e-mail address. Click **Send**. A test e-mail message is sent to the e-mail address to verify the connection.

After the SMTP server is added, the Add SMTP Server button is no longer available.

### What to do next Related tasks

"Scheduling a report" on page 272

You can schedule customized reports in IBM Spectrum Protect Plus to run at specific times.

### **Editing settings for an LDAP or SMTP server**

Edit the settings for an LDAP or SMTP server to reflect changes in your IBM Spectrum Protect Plus environment.

#### **Procedure**

To edit the settings for an LDAP or SMTP server, complete the following steps:

- 1. From the navigation menu, click System Configuration > LDAP/SMTP.
- 2. Click the edit icon / that is associated with the server.
  The edit pane is displayed.
- 3. Revise the settings for the server, and then click **Save**.

### **Deleting an LDAP or SMTP server**

Delete an LDAP or SMTP server when it becomes obsolete. Ensure that the server is not in use by IBM Spectrum Protect Plus before deleting the server.

#### **Procedure**

To delete an LDAP or SMTP server, complete the following steps:

- 1. From the navigation menu, click **System Configuration** > **LDAP/SMTP**.
- 2. Click the delete icon X that is associated with the server.
- 3. Click Yes to delete server.

## **Applying global preferences**

As the administrator, you can manage preferences that apply to all IBM Spectrum Protect Plus operations in the **Global Preferences** pane.

### Before you begin

Only the user with administrator credentials can manage global preferences.

**Restriction:** The deduplication table (DDT) options are available only if you install IBM Spectrum Protect Plus interim fix 10.1.4.222 or later.

#### **About this task**

The **Global Preferences** pane contains default values for parameters that apply to all IBM Spectrum Protect Plus operations. The preferences are organized into three categories: application, protection, and security.

The default values for the global preferences are shown in the following table.

Table 23. Default values for global preferences		
Preference	Default value	Unit (if applicable)
Concurrent Application Servers for Backup session	0	
vSnap Free Warn Percentage (%)	30	Percentage (%)
vSnap Free Error Percentage (%)	20	Percentage (%)
vSnap auto disable deduplication when dedup table (DDT) size exceeds resource limits	Checked	
vSnap DDT size limit in GB	50	Gigabytes
vSnap DDT size limit as percentage of total memory cache	80	Percentage (%)
Group VMs by VM Group size (GB)	5120	Gigabytes
Group VMs by Number of VMs in group	20	
VMware Connectin Timeout	300	Seconds
Backup Update Interval	300	Seconds
Password Minimum Length	8	Characters

You can change the default values in the **Global Preferences** pane.

#### **Procedure**

- 1. In the navigation pane, click **System Configuration** > **Global Preferences**.
- 2. Update the values for the global preferences. To revert to the default value from a previously entered value, click the reset icon S.

Preference	Description
Application	Concurrent Application Servers for Backup session  The maximum number of concurrent application servers per backup session.
Backup (Hypervisor / Application)	vSnap Free Warn Percentage (%)  The percentage threshold of remaining free space in the vSnap storage pool.  Warnings are displayed in the job log. For example, if a value of 10 is specified, a warning is displayed if the vSnap storage pool has 10% or less of remaining free space.
	vSnap Free Error Percentage (%)  The percentage threshold of remaining free space in the vSnap storage pool.  Errors are displayed in the job log. For example, if a value of 5 is specified, an error is displayed if the vSnap storage pool has 5% or less of remaining free space.
	vSnap auto disable deduplication when dedup table (DDT) size exceeds resource limits The deduplication table (DDT) is enabled by default. When either of the threshold limits defined by disk space (gigabytes) or percentage are exceeded, vSnap deduplication will be disabled. When deduplication is
	disabled, an alert is displayed.  vSnap DDT size limit in GB  The threshold in gigabytes (GB) of the vSnap deduplication table (DDT). The deduplication table (DDT) is disabled if the vSnap auto disable option is checked and the defined threshold is exceeded.
	vSnap DDT size limit as percentage of total memory cache The threshold as a percentage of the vSnap deduplication table (DDT) as compared to the total memory cache. The deduplication table (DDT) is disabled if the vSnap auto disable option is checked and the defined threshold is exceeded.
Hypervisor	Group VMs  Virtual machines can be grouped together. The group can be defined by a count of the VMs contained or the size of the VMs contained in the group.
	VMware Connection Timeout  The amount of time that IBM Spectrum Protect Plus waits for commands that are issued to connected vCenters to finish. If the operations do not finish within the specified amount of time, they are logged as errors. This setting applies only to VMware hypervisors.
	Backup Update Interval  The frequency at which messages about the progress of data transfer are updated in the job log.
Security	Password Minimum Length  The minimum length of passwords for IBM Spectrum Protect Plus. By default, the password has a minimum length of 8 characters, but you can specify a longer password. This value applies to all user accounts.

**Note:** For VM Grouping, there are four VM groups and each VM group can have a maximum of five VMs. Each group corresponds to one destination volume (data stream). A maximum of 20 VMs (4 data streams) can be done at a time based on size calculations.

## Logging on to the administrative console

Log on to the administrative console to review the configuration of the IBM Spectrum Protect Plus virtual appliance. Available information includes general system settings, network, and proxy settings.

#### **Procedure**

To log on to the administrative console, complete the following steps:

1. From a supported browser, enter the following URL:

https://HOSTNAME:8090/

Where HOSTNAME is the IP address of the virtual machine where the application is deployed.

2. In the login window, select one of the following authentication types in the **Authentication Type** list:

Authentication Type	Logon information
IBM Spectrum Protect Plus	To log on as an IBM Spectrum Protect Plus user with SYSADMIN privileges, enter your administrator user name and password.
System	To log on as a system user, enter the serveradmin password. The default password is sppDP758. You are prompted to change this password during the first logon.

#### What to do next

Review the configuration of the IBM Spectrum Protect Plus virtual appliance.

### **Related concepts**

"System requirements" on page 11

Before you install IBM Spectrum Protect Plus, review the hardware and software requirements for the product and other components that you plan to install in the storage environment.

"Managing roles" on page 279

Roles define the actions that can be completed for the resources that are defined in a resource group. While a resource group defines the resources that are available to an account, a role sets the permissions to interact with the resources.

# **Setting the time zone**

Use the Administrative Console to set the time zone of the IBM Spectrum Protect Plus appliance.

#### **Procedure**

To set the time zone, complete the following steps:

1. From a supported browser, enter the following URL:

https://HOSTNAME:8090/

Where HOSTNAME is the IP address of the virtual machine where the application is deployed.

2. In the login window, select one of the following authentication types in the **Authentication Type** list:

Authentication Type	Login information
<u> </u>	To log in as an IBM Spectrum Protect Plus user with SYSADMIN privileges, enter your administrator user name and password.

Authentication Type	Login information
System	To login as a system user, enter the serveradmin password. The default password is sppDP758. You are prompted to change this password during the first login.

- 3. Click Perform System Actions.
- 4. In the **Change Time Zone** section, select your time zone.

A message stating that the operation was successful displays. All IBM Spectrum Protect Plus logs and schedules will reflect the selected time zone. The selected time zone will also display on the IBM Spectrum Protect Plus appliance when logged in with the user ID **serveradmin**.

- 5. Restart the IBM Spectrum Protect Plus appliance from the Administrative Console.
- 6. Once the IBM Spectrum Protect Plus appliance has restarted, view the current time zone. Select **Product Information** from the main page of the Administrative Console and verify the updated time zone.

## Uploading an SSL certificate from the administrative console

To establish secure connections in IBM Spectrum Protect Plus, you can upload an SSL certificate such as an HTTPS or LDAP certificate by using the administrative console.

#### **About this task**

For HTTPS certificates, PEM encoded certificates with .cer or .crt extensions are supported.

For LDAP certificates, DER encoded certificates with .cer or .crt extensions are supported. If you are uploading an LDAP SSL certificate, ensure that IBM Spectrum Protect Plus has connectivity to the LDAP server and that the LDAP server is running.

ASCII and binary format certificates are accepted with the standard .pem, .cer, and .crt file extensions.

#### **Procedure**

To upload an SSL certificate, complete the following steps:

- 1. Contact your network administrator for the name of the certificate to export.
- 2. From a supported browser, export the certificate to your computer. Make note of the location of the certificate on your computer. The process of exporting certificates varies based on your browser.
- 3. From a supported browser, enter the following URL:

https://HOSTNAME:8090/

Where HOSTNAME is the IP address of the virtual machine where the application is deployed.

4. In the logon window, select one of the following authentication types in the Authentication Type list:

Authentication Type	Logon information
IBM Spectrum Protect Plus	To log on as an IBM Spectrum Protect Plus user with SYSADMIN privileges, enter your administrator user name and password.
System	To log on as a system user, enter the serveradmin password. The default password is sppDP758. You are prompted to change this password during the first logon.

- 5. Click Manage your certificates.
- 6. Click Browse, and select the certificate that you want to upload.
- 7. Click Upload SSL certificate for HTTPS.
- 8. Restart the virtual machine where the application is deployed.

## Logging on to the virtual appliance

Log on to the IBM Spectrum Protect Plus virtual appliance by using the vSphere Client to access the command line. You can access the command line in a VMware environment or in a Hyper-V environment.

### Accessing the virtual appliance in VMware

In a VMware environment, log on to the IBM Spectrum Protect Plus virtual appliance through vSphere Client to access the command line.

#### **Procedure**

Complete the following steps to access the virtual appliance command line:

- 1. In vSphere Client, select the virtual machine where IBM Spectrum Protect Plus is deployed.
- 2. On the **Summary** tab, select **Open Console** and click in the console.
- 3. Select **Login**, and enter your user name and password. The default user name is serveradmin and the default password is sppDP758.

#### What to do next

Enter commands to administer the virtual appliance. To log off, type exit.

## Accessing the virtual appliance in Hyper-V

In a Hyper-V environment, log on to the IBM Spectrum Protect Plus virtual appliance through vSphere Client to access the command line.

### **Procedure**

Complete the following steps to access the virtual appliance command line:

- 1. In Hyper-V Manager, select the virtual machine where IBM Spectrum Protect Plus is deployed.
- 2. Right-click the virtual machine and select **Connect**.
- 3. Select **Login**, and enter your user name and password. The default user name is serveradmin and the default password is sppDP758.

### What to do next

Enter commands to administer the virtual appliance. To log off, type exit.

## **Testing network connectivity**

The IBM Spectrum Protect Plus Service Tool tests host addresses and ports to determine if a connection can be established. You can use the Service Tool to verify whether a connection can be established between IBM Spectrum Protect Plus and a node

You can run the Service Tool from the IBM Spectrum Protect Plus command line or remotely by using a .jar file. If a connection can be established, the tool returns a green check mark. If a connection cannot be established, the error condition is displayed, along with possible causes and actions.

The tool provides guidance for the following error conditions:

- Timeout
- · Connection refused

- · Unknown host
- No route

### Running the Service Tool from a command line

You can start the Service Tool from the IBM Spectrum Protect Plus virtual appliance command line interface and run the tool in a web browser. Then, you can use the Service Tool to verify network connectivity between IBM Spectrum Protect Plus and a node.

#### **Procedure**

1. Log in to the IBM Spectrum Protect Plus virtual appliance by using the serveradmin user ID and access the command line. Run the following command:

```
# sudo bash
```

2. Open port 9000 on the firewall by running the following command:

```
# firewall-cmd --add-port=9000/tcp
```

3. Run the tool by running the following command:

```
# java -Dserver.port=9000 -jar /opt/ECX/spp/public/assets/tool/ngxdd.jar
```

4. To connect to the tool, enter the following URL in a browser:

```
http://hostname:9000
```

where hostname specifies the IP address of the virtual machine where the application is deployed.

5. To specify the node to test, complete the following fields:

#### Host

The hostname or IP address of the node that you want to test.

#### Port

The connection port to test.

- 6. Click Save.
- 7. To run the tool, hover the cursor over the tool, and then click **Run**.

If a connection cannot be established, the error condition is displayed, along with possible causes and actions.

8. Stop the tool by running the following command on the command line:

```
ctl-c
```

9. Protect your storage environment by resetting the firewall. Run the following commands:

```
# firewall-cmd --zone=public --remove-port=9000/tcp
# firewall-cmd --runtime-to-permanent
# firewall-cmd --reload
```

**Note:** If the firewall-cmd command is not available on your system, edit the firewall manually to add necessary ports and restart the firewall with iptables. For more information on editing firewall rules, see the **Firewall configuration with iptables** section here: <a href="https://www.ibm.com/support/knowledgecenter/en/STXKQY\_5.0.3/com.ibm.spectrum.scale.v5r03.doc/bl1adv\_firewallportopenexamples.htm">https://www.ibm.com/support/knowledgecenter/en/STXKQY\_5.0.3/com.ibm.spectrum.scale.v5r03.doc/bl1adv\_firewallportopenexamples.htm</a>.

### **Running the Service Tool remotely**

You can download the Service Tool as a .jar file from the IBM Spectrum Protect Plus user interface. Then, you can use the Service Tool to remotely test connectivity between IBM Spectrum Protect Plus and a node.

#### **Procedure**

1. In the IBM Spectrum Protect Plus user interface, click the user menu, and then click **Download Test Tool**.

A .jar file is downloaded to your workstation.

2. Launch the tool from a command-line interface. Java™ is only required on the system where the tool will be launched. Endpoints or target systems that are tested by the tool do not require Java.

The following command launches the tool in a Linux environment:

```
# java -jar -Dserver.port=9000 /<tool path >/ngxdd.jar
```

3. To connect to the tool, enter the following URL in a browser:

```
http://hostname:9000
```

where hostname specifies the IP address of the virtual machine where the application is deployed.

4. To specify the node to test, populate the following fields:

#### Host

The host name or IP address of the node that you want to test.

#### Port

The connection port to test.

- 5. Click **Save**.
- 6. To run the tool, hover the cursor over the tool, and then click the green **Run** button.

If a connection cannot be established, the error condition is displayed, along with possible causes and actions.

7. Stop the tool by issuing the following command on the command line:

ctl-c

# **Adding virtual disks**

You can add new virtual disks (hard disks) to your IBM Spectrum Protect Plus virtual appliance by using vCenter.

When you deploy the IBM Spectrum Protect Plus virtual appliance, you can deploy all virtual disks to one datastore that you specify at the time of deployment. You can add a disk within the virtual appliance and configure it as a Logical Volume Manager (LVM). You can then mount the new disk as a new volume or attach the new disk to the existing volumes within the virtual appliance.

You can review the disk partitions by using the **fdisk -1** command. You can review the physical volumes and the volume groups on the IBM Spectrum Protect Plus virtual appliance by using the **pvdisplay** and **vgdisplay** commands.

### Adding a disk to the virtual appliance

Use the vCenter client to edit the settings of the virtual machine.

#### Before you begin

To run commands, you must connect to the command line for the IBM Spectrum Protect Plus virtual appliance by using Secure Shell (SSH) and log in with the user ID serveradmin. The default initial password is sppDP758 and you are prompted to change the password when you log on for the first time.

#### **Procedure**

To add a disk to an IBM Spectrum Protect Plus virtual appliance, complete the following steps from the vCenter client:

- 1. From the vCenter client, complete the following steps:
  - a) On the **Hardware** tab, click **Add**.
  - b) Select Create a new virtual disk.
  - c) Select the required disk size. In the **Location** section, select one of the following options:
    - To use the current datastore, select Store with the virtual machine.
    - To specify one or more datastores for the virtual disk, select Specify a datastore or datastore cluster. Click Browse to select the new datastores.
  - d) In the **Advanced Options** tab, leave the default values.
  - e) Review and save your changes.
  - f) Click the **Edit Settings** option for the virtual machine to view the new hard disk.
- 2. Add the new SCSI device without rebooting the virtual appliance. From the console of the IBM Spectrum Protect Plus appliance, issue the following commands:

```
sudo bash
```

Press Enter.

```
echo "- - -" > /sys/class/scsi_host/host#/scan
```

Where # is the latest host number.

### Adding storage capacity from a new disk to the appliance volume

After you add a disk to the virtual appliance, you can attach the new disk to the existing volumes within the virtual appliance.

### Before you begin

To run commands, you must connect to the console of the IBM Spectrum Protect Plus virtual appliance by using SSH and log in with the user ID **serveradmin**. The default initial password is sppDP758 and you are prompted to change the password when you log in for the first time.

#### About this task

You need to complete this task only if you want to add the storage capacity from a new disk to an existing appliance volume. If you added the disk as a new volume, you do not need to complete this task.

#### **Procedure**

To add storage capacity from a new disk to the appliance volume, complete the following steps from the console of the virtual appliance:

- 1. Complete the following steps to set up a partition for the new disk and set the partition to be of type Linux LVM:
  - a) Open the new disk by using the **fdisk** command:

```
[serveradmin@localhost ~]# fdisk /dev/sdd
```

The **fdisk** utility starts in interactive mode. Output similar to the following output is displayed:

```
Device contains neither a valid DOS partition table, nor Sun, SGI or OSF disklabel
Building a new DOS disklabel with disk identifier 0xb1b293df.
Changes will remain in memory only, until you decide to write them.
After that, of course, the previous content won't be recoverable.
Warning: invalid flag 0x0000 of partition table 4 will be corrected by w(rite)
WARNING: DOS-compatible mode is deprecated. It's strongly recommended to
switch off the mode (command 'c') and change display units to sectors (command 'u').
Command (m for help):
```

a) At the **fdisk** command line, enter the **n** subcommand to add a partition.

```
Command (m for help): n
```

The following command action choices are displayed:

```
Command (m for help): n
Command action
e extended
p primary partition (1-4)
```

b) Enter the **p** command action to select the primary partition.

You are prompted for a partition number:

```
Command (m for help): n
Command action
e extended
p primary partition (1-4)
Partition number (1-4):
```

c) At the partition number prompt, enter the partition number 1.

```
Partition number (1-4): 1
```

The following prompt is displayed:

```
First cylinder (1-2610, default 1):
```

d) Do not type anything at the First cylinder prompt. Press the **Enter** key.

The following output and prompt is displayed:

```
First cylinder (1-2610, default 1):
Using default value 1
Last cylinder, +cylinders or +size{K,M,G} (1-2610, default 2610):
```

e) Do not type anything in the Last cylinder prompt. Press the **Enter** key.

The following output is displayed:

```
Last cylinder, +cylinders or +size{K,M,G} (1-2610, default 2610):
Using default value 2610
Command (m for help):
```

f) At the **fdisk** command line, enter the **t** subcommand to change a partition's system ID.

```
Command (m for help): t
```

You are prompted for a hex code that identifies the partition type:

```
Selected partition 1
Hex code (type L to list codes):
```

g) At the Hex code prompt, enter the hex code 8e to specify the Linux LVM partition type.

The following output is displayed:

```
Hex code (type L to list codes): 8e
Changed system type of partition 1 to 8e (Linux LVM)
Command (m for help):
```

h) At the **fdisk** command line, enter the **w** subcommand to write the partition table and to exit the **fdisk** utility.

```
Command (m for help): w
```

The following output is displayed:

```
Command (m for help): w (write table to disk and exit)
The partition table has been altered!
Calling ioctl() to re-read partition table.
Syncing disks.
```

- 2. To review the changes to the disk, issue the **fdisk -1** command.
- 3. To review the current list of Physical Volumes (PV), issue the **pvdisplay** command.
- 4. To create a new Physical Volume (PV), issue the **pvcreate /dev/sdd1** command.
- 5. To view the new PV from /dev/sdd1, issue the **pvdisplay** command.
- 6. To review the Volume Group (VG), issue the **vgdisplay** command.
- 7. To add the Physical Volume (PV) to the Volume Group (VG) and increase the space of the VG, issue the following command:

```
vgextend data_vg /dev/sdd1
```

- 8. To verify that data\_vg is extended, and that free space is available for logical volumes (or /data volume) to use, issue the **vgdisplay** command.
- 9. To review the Logical Volume (LV) /data volume, issue the **lvdisplay** command. The usage of the /data volume displays.
- To add the space of the LV /data volume to the total volume capacity, issue the lvextend command.

In this example, 20 GB of space is being added to a 100 GB volume.

```
[serveradmin@localhost ~]# lvextend -L120gb -r /dev/data_vg/data
Size of logical volume data_vg/data changed from 100.00 GiB to 120.00 GiB .

Logical volume data successfully resized
resize2fs 1.41.12 (date)
Filesystem at /dev/mapper/data_vg-data is mounted on /data; on-line
resizing required
old desc_blocks = 7, new_desc_blocks = 8
Performing an on-line resize of /dev/mapper/data_vg-data to 31195136
(4k) blocks.
The filesystem on /dev/mapper/data_vg-data is now 31195136 blocks
long.
```

After you run the preceding command, the size of the /data volume is displayed in **lvdisplay** command output as 120 GB:

```
[serveradmin@localhost ~]# lvdisplay
--- Logical volume ---
LV Path: /dev/data_vg/data
LV Name: data
VG Name: data vg
LV UUID: [uuid]
LV Write Access: read/write
LV Creation host, time localhost.localdomain, [date, time]
LV Status: available
# open: 1
LV Size: 120.00 GiB
Current LE: 30208
Segments: 2
Allocation inherit
Read ahead sectors: auto
- currently set to: 256
Block device: 253:1
[serveradmin@localhost ~]# df -h
Filesystem Size Used Avail Use% Mounted on
/dev/sda3 14G 2.6G 11G 20% /
tmpfs 16G 0 16G 0% /dev/shm
/dev/sda1 240M 40M 188M 18% /boot
/dev/mapper/data_vg-data
/lec/mapper/data2_vg-data
/lec/mapper/data2_vg-data
/lec/mapper/data2_vg-data2
```

# Chapter 12. Managing reports and logs

IBM Spectrum Protect Plus provides a number of predefined reports that you can customize to meet your reporting requirements. A log of actions that users complete in IBM Spectrum Protect Plus is also provided.

# **Types of reports**

You can customize predefined reports to monitor the utilization of backup storage and other aspects of your system environment.

Reports are based on the data that is collected by the most recent inventory job. You can generate reports after all cataloging jobs and subsequent database condense jobs are completed. You can run the following types of reports:

- · Backup storage utilization reports
- · Protection reports
- · System reports
- · Virtual machine environment reports

Reports include interactive elements, such as searching for individual values within a report, vertical scrolling, and column sorting.

### **Backup storage utilization reports**

IBM Spectrum Protect Plus provides backup storage utilization reports that display the storage utilization and status of your backup storage, such as vSnap servers.

To view backup storage utilization reports, complete the following steps:

- 1. In the navigation pane, click **Reports and Logs** > **Reports**.
- 2. Expand Backup Storage Utilization in the Reports pane.

The following reports are available:

#### **VM Backup Utilization**

Review the utilization of your virtual machine (VM) backups on backup storage, including the following data:

- The name of each VM, its location, and the associated hypervisor.
- The SLA policy that is used to protect the VM.
- The location of the backup storage. The backup storage can be the host name or IP address of a disk, the name of a cloud server, or the name of the repository server.
- The size of each VM backup.
- The number of restore points that are available for each VM.

For VMware virtual machines, to narrow your results to show VMs that have VMware tags, select one or more available tags in the **Tags** drop-down menu. The default value is **All**, which shows data for all VM backups.

#### **vSnap Storage Utilization Report**

Review the storage utilization of your vSnap servers, including the availability status, free space, and used space. The vSnap Storage Utilization report displays both an overview of your vSnap servers and a detailed view of the individual virtual machines and databases that are protected on each vSnap server.

Use the report options to filter specific vSnap servers to display. For a detailed view of the individual virtual machines and databases that are protected on each vSnap server, select **Show Resources** 

**protected per vSnap Storage**. This area of the report displays the names of the virtual machines, associated hypervisor, location, and the compression/deduplication ratio of the vSnap server.

Storage capacity and usage values that are displayed by IBM Spectrum Protect Plus might vary between those that appear on the dashboard versus those that appear on the vSnap Storage Utilization report. The dashboard displays live information, while the report reflects data from the last inventory job run. Variations are also due to differing rounding algorithms.

### **Related concepts**

"Report actions" on page 271

You can run, save, or schedule reports in IBM Spectrum Protect Plus.

"Types of reports" on page 267

You can customize predefined reports to monitor the utilization of backup storage and other aspects of your system environment.

### **Protection reports**

IBM Spectrum Protect Plus provides reports that display the protection status of your resources. By viewing the reports and taking any necessary action, you can help to ensure that your data is protected through user-defined recovery point objective parameters.

To view protection reports, complete the following steps:

- 1. In the navigation pane, click **Reports and Logs** > **Reports**.
- 2. Expand **Protection** in the **Reports** pane.

The following reports are available:

#### **Protected and Unprotected VMs report**

Run the Protected and Unprotected VMs report to view the protection status of your virtual machines. The report displays the total number of virtual machines added to the IBM Spectrum Protect Plus inventory before backup jobs are started.

Use the report options to filter by hypervisor type and to select specific hypervisors to display.

To exclude unprotected virtual machines in the report, select Hide Unprotected VMs.

To exclude virtual machines that are not backed up to secondary backup storage, select **Show only the VMs with Offloaded Backups**.

The **Summary View** displays an overview of your virtual machine protection status, including the number of unprotected and protected virtual machines and the managed capacity of the protected virtual machines. The managed capacity is the used capacity of a virtual machine. The **Detail View** provides further information about the protected and unprotected virtual machines, including names and location.

#### **Protected and Unprotected Databases report**

Run the Protected and Unprotected Databases report to view the protection status of your databases. The report displays the total number of databases added to the IBM Spectrum Protect Plus inventory before backup jobs are started.

Use the report options to filter by application type, application server, and application server type to display.

To exclude databases that are protected through hypervisor-based backup jobs, select **Hide Databases Protected as part of Hypervisor Backup**.

To exclude unprotected databases in the report, select **Hide Unprotected Databases**.

The **Summary View** displays an overview of your application server protection status, including the number of unprotected and protected databases, as well as the front end capacity of the protected databases. The front end capacity is the used capacity of a database. The **Detail View** provides further information about the protected and unprotected databases, included their names and location

#### **VM Backup History report**

Run the VM Backup History report to review the protection history of specific virtual machines. To run the report, at least one virtual machine must be specified in the **VMs** option. You can select multiple virtual machine names.

Use the report options to filter by failed or successful jobs and time of the last backup. The report can be further filtered by specific service level agreement (SLA) policies. In the **Detail View**, click the plus icon • next to an associated job to view job details, such as the reason why a job failed or the size of a successful backup.

### **Database Backup History report**

Run the Database Backup History report to review the protection history of specific databases. To run the report, at least one database must be specified in the **Databases** option. You can select multiple databases.

Use the report options to filter by failed or successful jobs and time of the last backup. The report can be further filtered by specific SLA policies. In **Detail View**, click the plus icon • next to an associated job to view further job details, such as the reason why a job failed or the size of a successful backup.

### **VM SLA Policy RPO Compliance report**

The VM SLA Policy RPO Compliance report displays virtual machines in relation to recovery point objectives as defined in SLA policies. The report displays the following information:

- Virtual machines in compliance
- Virtual machines not in compliance
- · Virtual machines in which the last backup job session failed

Use the report options to filter by hypervisor type and to select specific hypervisors to display. The report can be further filtered by virtual machines that are in compliance or not in compliance with the defined RPO.

#### **Database SLA Policy RPO Compliance report**

The Database SLA Policy RPO Compliance report displays databases in relation to recovery point objectives as defined in SLA policies. The report displays the following information:

- Databases in compliance
- Databases not in compliance
- Databases in which the last backup job session failed

Use the report options to filter by application type and to select specific application servers to display. The report can be further filtered by databases that are in compliance or not in compliance with the defined RPO, or by protection type, including data that was backed up to vSnap or by using replication.

#### **Related concepts**

"Types of reports" on page 267

You can customize predefined reports to monitor the utilization of backup storage and other aspects of your system environment.

### **System reports**

IBM Spectrum Protect Plus provides system reports that display an in-depth view of the status of your configuration, including storage system information, jobs, and job status.

To view system reports, complete the following steps:

- 1. In the navigation pane, click **Reports and Logs** > **Reports**.
- 2. Expand **System** in the **Reports** pane.

The following reports are available:

#### **Configuration report**

Review the configuration of the application servers, hypervisors, and backup storage that is available. Use the report options to filter the configuration types to display. The report displays the name of the resource, resource type, associated site, and the SSL connection status.

#### Job report

Review the available jobs in your configuration. Run the this report to view jobs by type, their average duration, and their successful run percentage. Use the report options to filter the job types to display and to display jobs that ran successfully over a period of time. The **Summary View** lists jobs by type along with the number of times a job session is run, completed, or failed. Job sessions listed as Other are jobs that are aborted, partially run, are currently running, skipped, or stopped. In the **Detail View**, click the plus icon • next to an associated job to view further job details such as virtual machines that are protected by a backup job, the average run time, and the next scheduled run time if the job is scheduled.

### **License report**

Review the configuration of your IBM Spectrum Protect Plus environment in relation to licensed features. The following sections and fields display in this report:

#### **Virtual Machine Protection**

The **Total Number of VMs** field displays the total number of virtual machines protected through hypervisor backup jobs, plus the number of virtual machines hosting application databases protected through application backup jobs (not hypervisor backup jobs). The **Front End Capacity** field displays the used size of these virtual machines.

#### **Physical Machine Protection**

The **Total Number of Physical Servers** field displays the total number of physical application servers hosting databases that are protected through application backup jobs. The **Front End Capacity** field displays the used size of these physical application servers.

### **Backup Storage Utilization (vSnap)**

The **Total Number of vSnap Servers** field displays the number of vSnap servers that are configured in IBM Spectrum Protect Plus as a backup destination. The **Target Capacity** field displays the total used capacity of the vSnap servers, excluding replica destination volumes.

### **Related concepts**

"Types of reports" on page 267

You can customize predefined reports to monitor the utilization of backup storage and other aspects of your system environment.

### VM environment reports

IBM Spectrum Protect Plus provides virtual machine environment reports to display the storage utilization and status of your virtual machines and datastores.

To view virtual machine environment reports, complete the following steps:

- 1. In the navigation pane, click **Reports and Logs > Reports**.
- 2. Expand VM Environment in the Reports pane.

The following reports are available:

#### **VM Datastores report**

Review the storage utilization of your datastores, including the total free space, provisioned space, and capacities. Run the this report to view your datastores, the number of virtual machines on the datastores, and the percentage of space available. Use the report options to filter by hypervisor type and to select specific hypervisors to display. The **Detail View Filter** controls the datastores to display in the **Detail View** based on the percentage of space used. Use the **Show Only Orphaned Datastores** filter to view datastores that do not have any virtual machines assigned to them, or virtual machines that are in an inaccessible state. The reason for a datastore to be in an orphaned state is displayed in the **Datastore** field in the **Detail View**.

#### **VM LUNs report**

Review the storage utilization of your virtual machine logical unit numbers (LUNs). Run this report to view your LUNs, associated datastores, capacities, and storage vendors. Use the report options to filter by hypervisor type and to select specific hypervisors to display. Use the **Show Only Orphaned Datastores** filter to view datastores that do not have any virtual machines assigned to them, or virtual machines that are in an inaccessible state.

#### **VM Snapshot Sprawl report**

This report report displays the age, name, and number of snapshots that are used to protect your Hypervisor resources. Use the report options to filter by hypervisor type and to select specific hypervisors to display. Use the **Snapshot Creation Time** filter to display snapshots from specific periods of time.

### **VM Sprawl report**

Review the status of your virtual machines, including virtual machines that are powered off, powered on, or suspended. Run this report to view unused virtual machines, the date and time when they were powered off, and virtual machine templates. Use the report options to filter by hypervisor type and to select specific hypervisors to display. The report can be further filtered by power state over time, including Days Since Last Powered Off and Days Since Last Suspended. The **Quick View** section displays a pie chart of used and free space on your virtual machines based on power state. Use the **Hypervisor** filter to display virtual machines on all hosts or a specific host. Information in the **Detail View** is categorized by power state. A separate table is provided for virtual machine templates.

### **VM Storage report**

Review your virtual machines and associated datastores in this report. View associated datastores and provisioned space of the datastores. Use the report options to filter by hypervisor type and to select specific hypervisors to display. The **Detail View** displays associated datastores and the amount of space on the datastore that is allocated for virtual disk files.

### **Related concepts**

"Types of reports" on page 267

You can customize predefined reports to monitor the utilization of backup storage and other aspects of your system environment.

# **Report actions**

You can run, save, or schedule reports in IBM Spectrum Protect Plus.

### **Running a report**

You can run IBM Spectrum Protect Plus reports with default parameters or run customized reports with custom parameters.

### Before you begin

Custom roles that are assigned to users that run reports require that the appropriate permissions be set on that role so that the report can be viewed. For more information about roles, permission types, and permissions, see "Managing roles" on page 279.

### **Procedure**

To run a report, complete the following steps:

- 1. In the navigation pane, click **Reports and Logs** > **Reports**.
- 2. Expand a report type and select a report to run.
- 3. Run the report either with custom parameters or default parameters:
  - To run the report with custom parameters, set the parameters in the **Options** section, and click **Run**. Parameters are unique to each report.

• To run the report with default parameters, click **Run**.

#### What to do next

Review the report in the **Reports** pane.

### **Related concepts**

"Managing reports and logs" on page 267

IBM Spectrum Protect Plus provides a number of predefined reports that you can customize to meet your reporting requirements. A log of actions that users complete in IBM Spectrum Protect Plus is also provided.

### Creating a custom a report

You can modify predefined reports with custom parameters in IBM Spectrum Protect Plus and save the customized reports.

#### **Procedure**

To create a report, complete the following steps:

- 1. In the navigation pane, click **Reports and Logs** > **Reports**.
- 2. Select a predefined report.
- 3. Set your customized parameters.
- 4. Define the report to run in one of the following circumstances:
  - · Run on demand.
  - Create a schedule to run the report as defined by the parameters of the schedule.
- 5. Save the report with a customized name.

#### What to do next

Run the report and review the report in the **Reports** pane.

#### **Related concepts**

"Managing reports and logs" on page 267

IBM Spectrum Protect Plus provides a number of predefined reports that you can customize to meet your reporting requirements. A log of actions that users complete in IBM Spectrum Protect Plus is also provided.

### Scheduling a report

You can schedule customized reports in IBM Spectrum Protect Plus to run at specific times.

#### **Procedure**

To schedule a report, complete the following steps:

- 1. In the navigation pane, click Reports and Logs > Reports.
- 2. Select a report type.
- 3. Select the report that you want to schedule.
- 4. Edit the report parameters in the **Options** section,
- 5. Enter values in the **Name** and **Description** fields for the report.
- 6. Set the parameters for the report.
- 7. In the Schedule Report section, click Define Schedule.
- 8. Define a trigger for the report.
- 9. Enter an address to receive the scheduled report in the email field, and then click Add a recipient.
- 10. Click Save.

#### What to do next

After the report runs, the recipient can review the report, which is delivered by email.

#### **Related concepts**

"Managing reports and logs" on page 267

IBM Spectrum Protect Plus provides a number of predefined reports that you can customize to meet your reporting requirements. A log of actions that users complete in IBM Spectrum Protect Plus is also provided.

## **Collecting audit logs for actions**

You can collect audit logs and search for actions that are completed in IBM Spectrum Protect Plus.

#### **Procedure**

To collect audit logs:

- 1. In the navigation pane, click **Reports and Logs** > **Audit Logs**.
- 2. Review a log of actions that were completed in IBM Spectrum Protect Plus. Information includes the users who completed the actions and descriptions of the actions.
- 3. To search for the actions of a specific user in IBM Spectrum Protect Plus, enter the user name in the user search field.
- 4. Optional: Expand the **Filters** section to further filter the displayed logs. Enter specific action descriptions and a date range in which the action was completed.
- 5. Click the search icon Q.
- 6. To download the audit log as a .csv file, click **Download**, and then select a location to save the file.

#### **Related concepts**

"Managing user accounts" on page 283

Before a user can log on to IBM Spectrum Protect Plus and use the available functions, a user account must be created in IBM Spectrum Protect Plus.

# Enabling the display of alerts in the system log

Alerts that are generated by IBM Spectrum Protect Plus can be logged to the system log. After you enable this feature, you can search the system log to find alerts.

#### **About this task**

An alert list in the IBM Spectrum Protect Plus user interface displays errors and warnings, which can help you to identify and resolve issues. Each item in the alert list includes a status icon, a summary of the issue, and a link to associated logs. These alerts can also be logged to the system log on the IBM Spectrum Protect Plus appliance.

#### **Procedure**

To enable logging of IBM Spectrum Protect Plus alerts to the system log, complete the following steps:

- 1. Ensure that there are no running jobs on the IBM Spectrum Protect Plus appliance.
- 2. Stop the Virgo service by issuing the following command:

sudo systemctl stop virgo

- 3. Log in to the IBM Spectrum Protect Plus appliance by using the Secure Shell (SSH) protocol.
- 4. Open the persistence properties file in the following directory:

/opt/virgo/repository/ecx-usr/com.syncsort.dp.xsb.persistence.properties

**Tip:** You can edit the persistence properties file by using the vi text editor, which is packaged along with the IBM Spectrum Protect Plus appliance.

5. Set the alertInSystemLogNessages variable to yes:

```
mongodb.alertInSystemLogMessages=yes
```

- 6. Save the properties file.
- 7. Restart the Virgo service by issuing the following command:

```
sudo systemctl start virgo
```

#### **Results**

Alerts are logged to the system log.

### Example

```
[root@veguardian-cb3 log]# grep SPPAlert /var/log/messages
Jan 25 23:53:03 veguardian-cb3 virgo[993]: ERROR [SPPAlert]
vmware_Offload_Protect:1548460344227 Job vmware_Offload_Protect (id=1006,
session=1,548,460,344,227) failed.
```

Note: The following format is used for alerts that are logged by IBM Spectrum Protect Plus:

*Message\_type*: The type can be ERROR, WARNING, and other types.

*Message\_source*: Indicates the source of the message. This appears as SPPAlert for IBM Spectrum Protect Plus messages.

Message\_text: Contains the IBM Spectrum Protect Plus alert details.

#### What to do next

Optionally, to search for an alert, log in to the IBM Spectrum Protect Plus appliance and search for SPPalert.

# Chapter 13. Managing user access

By using role-based access control, you can set the resources and permissions available to IBM Spectrum Protect Plus user accounts.

You can tailor IBM Spectrum Protect Plus for individual users, giving them access to the features and resources that they require.

Once resources are available to IBM Spectrum Protect Plus, they can be added to a resource group along with high-level IBM Spectrum Protect Plus items such as a hypervisor and individual screens.

Roles are then configured to define the actions that can be performed by the user associated with the resource group. These actions are then associated with one or more user accounts.

Use the following sections of the **Accounts** pane to configure role-based access:

### **Resource Groups**

A resource group defines the resources that are available to a user. Every resource that is added to IBM Spectrum Protect Plus can be included in a resource group, along with individual IBM Spectrum Protect Plus functions and screens. By defining resource groups, you can fine tune the user experience. For example, a resource group could include an individual hypervisor, with access to only backup and reporting functionality. When the resource group is associated with a role and a user, the user will see only the screens that are associated with backup and reporting for the assigned hypervisor.

**Restriction:** Do not assign a role-based access control (RBAC) user to more than one VMware resource group. Users that have been assigned to the Tag and Categories resource group and then are also assigned to either Hosts and Clusters or VMs and Templates will result in data not being displayed for the Hosts and Clusters view or the VMs and Templates view. Only information for Tags and Categories will be displayed when that is selected as a view when performing operations.

#### Roles

Roles define the actions that can be performed on the resources that are defined in a resource group. While a resource group defines the resources that will be made available to a user account, a role sets the permissions to interact with the resources defined in the resource group. For example, if a resource group is created that includes backup and restore jobs, the role determines how a user can interact with the jobs.

Permissions can be set to allow a user to create, view, and run the backup and restore jobs that are defined in a resource group, but not delete them. Similarly, permissions can be set to create administrator accounts, allowing a user to create and edit other accounts, set up sites and resources, and interact with all of the available IBM Spectrum Protect Plus features.

#### **User accounts**

A user account associates a resource group with a role. To enable a user to log in to IBM Spectrum Protect Plus and use its functions, you must first add the user as an individual user (referred to as a native user) or as part of an imported group of LDAP users, and then assign resource groups and roles to the user account. The account will have access to the resources and features that are defined in the resource group as well as the permissions to interact with the resources and features that are defined in the role.

## Managing user resource groups

A resource group defines the resources are made available to a user. Every resource added to IBM Spectrum Protect Plus can be included in a resource group, along with individual IBM Spectrum Protect Plus functions and screens.

### **Creating a resource group**

Create a resource group to define the resources that are available to a user.

#### Before you begin

You may not assign more than one application per machine as an application server to a resource group. For example, if SQL and Exchange occupy the same machine and both are registered with IBM Spectrum Protect Plus, only one of those can be added as an application server to a given resource group.

#### **Procedure**

To create a resource group, complete the following steps:

- 1. In the navigation pane, click **Accounts** > **Resource Group**.
- 2. Click Create Resource Group. The Create Resource Group pane displays.
- 3. Enter a name for the resource group.
- 4. From the I would like to create a resource group menu, select one of the following options:

Option	Actions
New	<ul> <li>a. Select a resource type from the Choose a resource type menu.</li> <li>b. Select resource subtypes, and then click Add Resources. Resources are added to the Selected Resources view.</li> </ul>
From template	a. Select a resource group from the Which resource group would you like to use as a template? list. Resources from the selected template are added to the Selected Resources view.
	b. You can add resources by using the <b>Choose a resource type</b> list and its associated lists.
	To view available resource types and their usage, see "Resource types" on page 277.

If you want to delete resources from the group, click the delete icon that is associated with a resource or click **Delete All** to delete all resources.

5. When you are finished adding resources, click Create resource group.

#### Results

The resource group displays in the resource group table and can be associated with new and existing user accounts.

#### What to do next

After you add the resource group, complete the following action:

Action	How to
Create roles to define the actions that can be performed by the user account that is associated with the resource group. Roles are used to define permissions to interact with the resources that are defined in the resource group.	See <u>"Creating a role" on page 280</u> .

**Resource types**Resource types are selected when resource groups are created and determine the resources that are available to a user assigned to a group.

The following resource types and subtypes are available:

Resource Type	Subtype	Description
Accounts	<ul><li>Role</li><li>User</li><li>Identity</li></ul>	Used to grant access to roles and users through the <b>Accounts</b> pane.
Application	<ul><li>Db2</li><li>Oracle</li><li>SQL Standalone/Failover Cluster</li><li>SQL Always On</li></ul>	Used to grant access to viewing individual application databases on an application server in IBM Spectrum Protect Plus.
Application Server	• Db2 • SQL • Oracle	Used to grant access to application servers in IBM Spectrum Protect Plus without access to individual databases.
Hypervisor	<ul><li>VMware</li><li>Hyper-V</li></ul>	Used to grant access to hypervisor resources.
Job	None	Used to grant access to Inventory, Backup, and Restore jobs. The Job resource group is mandatory for all Backup and Restore operations, including assigning SLA Policies to resources.
Report	<ul><li>Backup Storage Utilization</li><li>Protection</li><li>System</li><li>VE Environment</li></ul>	Used to grant access to report types and individual reports.
Screen	None	Used to grant or deny access to screens in the IBM Spectrum Protect Plus interface. If certain screens are not included in a resource group for a user, the user will not be able to access the functionality provided on the screen, regardless of the permissions granted to the user.

Resource Type	Subtype	Description
SLA Policy	None	Used to grant access to SLA Policies for Backup operations.
System	Identity	Used to grant access to the credentials required to access your resources. Identity functionality is available through the <b>System</b> > <b>Identity</b> pane.
System Configuration	Disk	Used to grant access to vSnap backup storage servers.
System Configuration	LDAP	Used to grant access to LDAP servers for user registration.
System Configuration	Logs	Used to grant access to viewing and downloading Audit and System logs.
System Configuration	Script	Used to grant access to uploaded prescripts and postscripts.
System Configuration	Script Server	Used to grant access to script servers, where scripts are run during a Backup or Restore job.
System Configuration	Site	Used to grant access to sites, which are assigned to vSnap backup storage servers.
System Configuration	SMTP	Used to grant access to SMTP servers for job notifications.
System Configuration	VADP Proxy	Used to grant access to VADP proxy servers.

# **Editing a resource group**

You can edit a resource group to change the resources and features that are assigned to the group. Updated resource group settings take effect when user accounts that are associated with the resource group log in to IBM Spectrum Protect Plus.

# Before you begin

Note the following considerations before editing a resource group:

- If you are signed in when the permissions or access rights for your user account are changed, you must sign out and sign in again for the updated permissions to take effect.
- You can edit any resource group that is not designated as Cannot be modified.

You may not assign more than one application per machine as an application server to a resource group. For example, if SQL and Exchange occupy the same machine and both are registered with IBM Spectrum Protect Plus, only one of those can be added as an application server to a given resource group.

# **Procedure**

To edit a resource group, complete the following steps:

- 1. In the navigation pane, click **Accounts** > **Resource Group**.
- 2. Select a resource group and click the options icon \*\*\* for the resource group. Click **Modify resources**.
- 3. Revise the resource group name, resources, or both.

4. Click Update Resource Group.

# Deleting a resource group

You can delete any resource group that is not designated as **Cannot be modified**.

#### **Procedure**

To delete a resource group, complete the following steps:

- 1. In the navigation pane, click **Accounts** > **Resource Group**.
- 2. Select a resource group and click the options icon \*\*\* for the resource group. Click **Delete resource** group.
- 3. Click Yes.

# **Managing roles**

Roles define the actions that can be completed for the resources that are defined in a resource group. While a resource group defines the resources that are available to an account, a role sets the permissions to interact with the resources.

For example, if a resource group is created that includes backup and restore jobs, the role determines how a user can interact with the jobs. Permissions can be set to allow a user to create, view, and run the backup and restore jobs that are defined in a resource group, but not delete them.

Similarly, permissions can be set to create administrator accounts, allowing a user to create and edit other accounts, set up sites and resources, and interact with all of the available IBM Spectrum Protect Plus features.

The functionality of a role is dependent on a properly configured resource group. When selecting a predefined role or configuring a custom role, you must ensure that access to necessary IBM Spectrum Protect Plus operations, screens, and resources align with the proposed usage of the role.

The following user account roles are available:

# **Application Admin**

The Application Admin role allows users to complete the following actions:

- Register and modify application database resources that are delegated by an administrator.
- Associate application databases to assigned SLA policies.
- · Complete backup and restore operations.
- Run and schedule reports to which the user has access.

Access to resources must be granted by an administrator through the **Accounts** > **Resource Groups** pane.

#### **Backup Only**

The Backup Only role allows users to complete the following actions:

- · Create, view, and run backup operations
- · View, create, and edit SLA policies to which the user has access

Access to resources, including specific backup jobs, must be granted by an administrator by clicking **Accounts > Resource Groups**.

#### **Restore Only**

The Restore Only role allows users to complete the following actions:

- Run, edit, and monitor restore operations.
- View, create, and edit SLA Policies to which the user has access.

Access to resources, including specific restore jobs, must be granted by an administrator through the **Accounts** > **Resource Groups** pane.

#### **Self Service**

The Self Service role allows users to monitor existing backup and restore operations that are delegated by an administrator.

Access to resources, including specific jobs, must be granted by an administrator through the **Accounts** > **Resource Groups** pane.

#### **SYSADMIN**

The SYSADMIN role is the administrator role. This role provides access to all resources and privileges. Users with this role can add users and complete the following actions for all users other than the admin user:

- · Modify and delete user accounts
- Change user passwords
- · Assign user roles

An administrator can also access the administrative console by selecting **IBM Spectrum Protect Plus** from the **Authentication Type** list in the console login window and entering administrator credentials.

From the administrative console, the administrator can apply software updates, restart the IBM Spectrum Protect Plus appliance, and set the local time zone.

For more information about using the Administrative Console, see <u>"Logging on to the administrative console"</u> on page 257.

#### **VM Admin**

The VM Admin role allows a users to complete the following actions:

- Register and modify hypervisor resources to which the user has access.
- · Associate hypervisors to SLA policies.
- Complete backup and restore operations.
- Run and schedule reports to which the user has access.

Access to resources must be granted by an administrator through the **Accounts** > **Resource Groups** pane.

# **Creating a role**

Create roles to define the actions that can be completed by the user of an account that is associated with a resource group. Roles are used to define permissions to interact with the resources that are defined in the resource group.

## **Procedure**

To create a user role, complete the following steps:

- 1. In the navigation pane, click **Accounts** > **Role**.
- 2. Click Create Role. The Create Role pane displays.
- 3. From the I would like to create a role list, select one of the following options:

Option	Actions
New	Select permissions to apply to the role. By default, none of the permissions are pre-selected.
From template	a. Select a role from the Which role would you like to use as a template? menu. Permissions that are associated with the template role are selected by default.
	b. Select additional permissions to apply to the role, and delete permissions that are not required.

Option	Actions
	To view available permissions and their usage, see "Permission types" on page 281.

4. Enter a name for the role, and then click **Create Role**.

# Results

The new role is displayed in the roles table and can be applied to new and existing user accounts.

# **Permission types**

Permission types are selected when user accounts are created and determine the permissions that are available to the user.

The following permissions are available:

Name	Permissions	Description
Application	View	Used to view individual application databases on an application server in IBM Spectrum Protect Plus.
Application Server	Register, view, edit, deregister	Used to interact with application servers, such as SQL or Oracle servers, without access to individual databases.
Certificate	Create, view, edit, delete	Used to interact with SSL certificates to access Cloud Servers.
Cloud	Register, view, edit, deregister	Used to interact with Cloud Servers that are defined as backup storage for offloads.
Hypervisor	Register, view, edit, deregister, options	Used to interact with hypervisor virtual machines, such as VMware or Hyper-V virtual machines.
Identity and Keys	Create, view, edit, delete	Used to interact with the credentials required to access your resources. Identity functionality is available through the Accounts > Identities pane.
LDAP	Register, view, edit, deregister	Used to interact with LDAP servers for user registration.
Log	View	Used to view Audit and System logs.
Job	Create, view, edit, run, delete	Used to interact with Inventory, Backup, and Restore jobs. Note: If the user has permission to Run a job, then they also can Hold, Release, and Perform custom restore actions for the job
VADP Proxy	Register, view, edit, deregister	Used to interact with VADP
Report	Create, view, edit, delete	Used to interact with reports.

Name	Permissions	Description
Resource Group	Create, view, edit, delete	Used to interact with resource groups, which define the IBM Spectrum Protect Plus resources that are made available to a user.
Role	Create, view, edit, delete	Used to interact with roles, which define the actions that can be performed on the resources defined in a resource group.
Script	Upload, view, replace, delete	Used to interact with prescripts and postscripts that are added to IBM Spectrum Protect Plus and run before or after a job.
Site	Create, view, edit, delete	Used to interact with sites, which are assigned to vSnap backup storage servers.
SMTP	Register, view, edit, deregister	Used to interact with SMTP servers for job notifications.
Backup Storage	Register, view, edit, deregister	Used to interact with vSnap backup storage servers.
SLA Policy	Create, view, edit, delete	Used to interact with SLA Policies, which allow users to create customized templates for Backup jobs.
User	Create, view, edit, delete	Used to interact with users, which associated a resource group with a role, and provides access to the IBM Spectrum Protect Plus user interface.

# **Editing a role**

You can edit a role to change the resources and permissions that are assigned to the role. Updated role settings take effect when user accounts that are associated with the role log in to IBM Spectrum Protect Plus.

# Before you begin

Note the following considerations before editing a role:

- If you are signed in when the permissions or access rights for your user account are changed, you must sign out and sign in again for the updated permissions to take effect.
- You can edit any role that is not designated as **Cannot be modified**.

# **Procedure**

To edit a user role, complete the following steps

- 1. In the navigation pane, click **Accounts** > **Role**.
- 2. Select a role and click the options icon \*\*\* for the role. Click **Modify Role**.
- 3. Revise the role name, permissions, or both.
- 4. Click Update role.

# **Deleting a role**

You can delete a role that is not designated as **Cannot be modified**.

#### **Procedure**

To delete a role, complete the following steps:

- 1. In the navigation pane, click **Accounts** > **Role**.
- 2. Select a role and click the options icon \*\*\* for the role. Click **Delete role**.
- 3. Click Yes.

# **Managing user accounts**

Before a user can log on to IBM Spectrum Protect Plus and use the available functions, a user account must be created in IBM Spectrum Protect Plus.

# Creating a user account for an individual user

Add an account for an individual user in IBM Spectrum Protect Plus. If you are upgrading from a version of IBM Spectrum Protect Plus that is earlier than 10.1.1, permissions assigned to users in the previous version must be reassigned in IBM Spectrum Protect Plus.

# Before you begin

If you want to use custom roles and resource groups, create them before you create a user. See "Creating a resource group" on page 276 and "Creating a role" on page 280.

#### **Procedure**

To create an account for an individual user, complete the following steps:

- 1. In the navigation pane, click **Accounts** > **User**.
- 2. Click Add User. The Add User pane is displayed.
- 3. Click Select the type of user or group you want to add > Individual new user.
- 4. Enter a name and password for the user.
- 5. In the **Assign Role** section, select one or more roles for the user.
- 6. In the **Permission Groups** section, review the permissions and resources that are available to the user, and then click **Continue**.
- 7. In the **Add Users Assign Resources** section, assign one or more resource groups to the user, and then click **Add resources**.

The resource groups are added to the **Selected Resources** section.

8. Click Create user.

# Results

The user account is displayed in the users table. Select a user from the table to view available roles, permissions, and resource groups.

# Creating a user account for an LDAP group

Add a user account for an LDAP group to IBM Spectrum Protect Plus.

# Before you begin

Review the following procedures before you create a user account for an LDAP group:

• Register an LDAP provider in IBM Spectrum Protect Plus. See "Adding an LDAP server" on page 252.

• If you want to use custom roles and resource groups, create them before you create a user. See "Creating a resource group" on page 276 and "Creating a role" on page 280.

#### **Procedure**

Complete the following steps to create a user account for an LDAP group:

- 1. In the navigation pane, click **Accounts** > **User**.
- 2. Click Add User. The Add User pane is displayed.
- 3. Click Select the type of user or group you want to add > LDAP Group.
- 4. Select an LDAP group.
- 5. In the **Assign Role** section, select one or more roles for the user.
- 6. In the **Permission Groups** section, review the permissions and resources that are available to the user, and then click **Continue**.
- 7. In the **Add Users Assign Resources** section, assign one or more resource groups to the user, and then click **Add resources**.

The resource groups are added to the **Selected Resources** section.

8. Click Create user.

#### **Results**

The user account is displayed in the users table. Select a user from the table to view available roles, permissions, and resource groups.

# Editing a user account

You can edit the user name, password, associated resource groups, and roles for a user account, with the exception of users who are assigned to the SUPERUSER role. If a user is a member of the SUPERUSER role, you can change only the password for the user.

# Before you begin

If you are signed in when the permissions or access rights for your user account are changed, you must sign out and sign in again for the updated permissions to take effect.

# **Procedure**

Complete the following steps to edit the credentials of a user account:

- 1. In the navigation pane, click **Accounts** > **User**.
- 2. Select one or more users. If you select multiple users with different roles, you can modify only their resources and not their roles.
- 3. Click the options icon \*\*\* to view available options. The options that are shown depend on the selected user or users.

# **Modify settings**

Edit the user name and password, associated roles, and resource groups.

# **Modify resources**

Edit the associated resource groups.

4. Modify the settings for the user, and then click **Update user** or **Assign resources**.

# Deleting a user account

You can delete any user account, with the exception of users who are assigned to the SUPERUSER role.

# **Procedure**

To delete a user account, complete the following steps:

1. In the navigation pane, click **Accounts** > **User**.

- 2. Select a user.
- 3. Click the options icon \*\*\*\*, and then click **Delete user**.

# **Managing identities**

Some features in IBM Spectrum Protect Plus require credentials to access your resources. For example, IBM Spectrum Protect Plus connects to Oracle servers as the local operating system user that is specified during registration to complete tasks like cataloging, data protection, and data restore.

User names and passwords for your resources can be added and edited through the **Identity** pane. Then when utilizing a feature in IBM Spectrum Protect Plus that requires credentials to access a resource, select **Use existing user**, and select an identity from the drop-down menu.

# Adding an identity

Add an identity to provide user credentials.

#### **Procedure**

To add an identity, complete the following steps:

- 1. In the navigation pane, click **Accounts > Identity**.
- 2. Click Add Identity.
- 3. Complete the fields in the **Identity Properties** pane:

#### Name

Enter a meaningful name to help identify the identity.

#### Username

Enter the user name that is associated with a resource, such as an SQL or Oracle server.

#### **Password**

Enter the password that is associated with a resource.

4. Click Save.

The identity displays in the identities table and can be selected when you are using a feature that requires credentials to access a resource through the **Use existing user** option.

# **Editing an identity**

You can revise an identity to change the user name and password used to access an associated resource.

#### **Procedure**

To edit an identity, complete the following steps:

- 1. In the navigation pane, click **Accounts > Identity**.
- 2. Click the edit icon / that is associated with an identity.

The **Identify Properties** pane displays.

- 3. Revise the identity name, user name, and password.
- 4. Click Save.

The revised identity displays in the identities table and can be selected when utilizing a feature that requires credentials to access a resource through the **Use existing user** option.

# **Deleting an identity**

You can delete an identity when it becomes obsolete. If an identity is associated with a registered application server, it must be removed from the application server before it can be deleted. To remove the

association, navigate to the **Backup** > **Manage Application Servers** page associated with the application server type, then edit the settings of the application server.

# **Procedure**

To delete an identity, complete the following steps:

- 1. In the navigation pane, click **Accounts** > **Identity**.
- 2. Click the delete icon  $\times$  that is associated with an identity.
- 3. Click **Yes** to delete the identity.

# **Chapter 14. Licensing**

License auditing in IBM Spectrum Protect Plus is enabled by default to determine if the current usage is within license entitlement levels and to prevent potential license violations.

IBM Spectrum Protect Plus generates entitlement audit logs as IBM® Software License Metric Tag (.slmtag) files. IBM® License Metric Tool (ILMT) is then used to translate the file and generate License Consumption Reports. Use the information in this section to interpret your .slmtag files.

# **Software License Metric (SLM) tags**

IBM Spectrum Protect Plus generates entitlement audit logs as IBM® Software License Metric Tag (.slmtag) files. IBM® License Metric Tool (ILMT) is then used to translate the file and generate License Consumption Reports. Use the provided information to interpret your .slmtag files.

The .slmtag files can store information up to a maximum file size of 1 MB, after which the file is archived and a new log file is created. A maximum of 10 log files are kept.

**Upgrade requirements:** If you are upgrading to IBM Spectrum Protect Plus 10.1.3 from a prior release, you must run the maintenance job to generate the .slmtag files. For future upgrades, you must run the maintenance job to update existing .slmtag files.

# Log format

The .slmtag files are stored in XML format, with new metric records appended to the end of the file.

The following is a sample .slmtag file:

```
<SchemaVersion>2.1.1</SchemaVersion>
<SoftwareIdentity>
   <SoftwareIdentity name>"IBM Spectrum Protect Plus"</Name>
   <InstanceId>/opt/virgo</InstanceId>
</softwareIdentity>
<Metric logTime ="2018-11-05T16:05:09+00:00">
   <Type>HYPERVISOR_SERVER_COUNT</Type>
   <SubType>HYPERVISOR_SERVER_COUNT</SubType>
   <Value>0</Value>
   <Period>
    <StartTime>2018-11-05T16:05:09+00:00</StartTime>
    <EndTime>2018-11-05T16:05:09+00:00</EndTime>
   </Period>
</Metric>
<Metric logTime="2018-11-05T16:05:09+00:00">
   <Type>APPLICATION_INSTANCE_COUNT</Type>
   <SubType>APPLICATION_INSTANCE_COUNT</SubType>
   <Value>0</Value>
   <Period>
    <StartTime>2018-11-05T16:05:09+00:00</StartTime>
    <EndTime>2018-11-05T16:05:09+00:00</EndTime>
   </Period>
</Metric>
```

where the Value element displays the number of hosts in all the resource groups with packages deployed for an instance group, at the specified time in the EndTime element.

The file grows over time and may be edited to remove older metric elements. Ensure that you retain elements long enough for ILMT scanning; the scanning frequency is determined by the ILMT administrator, but generally it should be sufficient to keep elements for a month.

# Log location

The .slmtag file is located in the /data/slmtag directory.

# **Related concepts**

"Job types" on page 231

Jobs are used to run backup, restore, maintenance, and inventory operations in IBM Spectrum Protect Plus.

#### **Related tasks**

"Starting jobs" on page 232

You can run any job on demand, even if the job is set to run on a schedule.

# **Integration with IBM License Metric Tool (ILMT)**

Use IBM License Metric Tool (ILMT) to help determine whether your system environment is compliant with licensing requirements.

ILMT provides useful features for managing virtualized environments and measuring license utilization. ILMT discovers the software that is installed in your infrastructure, helps you to analyze the consumption data, and allows you to generate audit reports. Each report provides you with different information about your infrastructure, for example the computer groups, software installations, and the content of your software catalog.

By default, every ILMT audit report presents data from the previous 90 days. You can customize the type and amount of information displayed in a report by using filters, and save your personal settings for future use. You can also export the reports to .csv or .pdf format, and schedule report emails so that specified recipients are notified when important events occur.

For more information, see the IBM License Metric Tool product documentation.

# **Chapter 15. Troubleshooting**

Troubleshooting procedures are available for problem diagnosis and resolution.

For a list of known issues and limitations for each IBM Spectrum Protect Plus release, see  $\underline{\text{technote}}$  2014120.

# **Collecting log files for troubleshooting**

To troubleshoot the IBM Spectrum Protect Plus application, you can download an archive of log files that are generated by IBM Spectrum Protect Plus.

#### **Procedure**

To collect log files for troubleshooting, complete the following steps:

- 1. Click the user menu, and then click **Download System Logs**. The download process may take some time to complete.
- 2. Open or save the file log zip file, which contains individual log files for different IBM Spectrum Protect Plus components.

For information about log files, see the protecting applications or protecting hypervisors backup sections.

## What to do next

To troubleshoot issues, complete the following steps:

- 1. Analyze the log files and take appropriate actions to resolve the issue.
- 2. If you cannot resolve the issue, submit the log files to IBM Software Support for assistance.

# **Chapter 16. Product messages**

IBM Spectrum Protect Plus components send messages with prefixes that help to identify which component they come from. Use the search option to find a particular message by using its unique identifier.

Messages consist of the following elements:

- · A five-letter prefix.
- A number to identify the message.
- Message text that is displayed on screen and written to message logs.

**Tip:** Use your browser's search capability by using Ctrl+F to find the message code you are looking for.

The following example contains the Db2 agent prefix. When you click More, extra details that explain the reason for the message are shown.

```
Warning
Apr 16, 2019
9:14:37 AM
GTGGH0098
[myserver1.myplace.irl.ibm.com]
Database AC7 will not be backed up as it is ineligible for the backup operation. More
```

# **IBM Spectrum Protect Plus message prefixes**

Messages have different prefixes to help you to identify the component that issues the message.

The following table identifies the prefix that is associated with each component.

Table 24. Messages prefixes by component	
Prefix	Component
CTGGA	IBM Spectrum Protect Plus
CTGGE	IBM Spectrum Protect Plus for Microsoft SQL Server
CTGGF	IBM Spectrum Protect Plus for Oracle
CTGGG	IBM Spectrum Protect Plus for Microsoft Exchange Server
стадн	IBM Spectrum Protect Plus for IBM Db2
CTGGI	IBM Spectrum Protect Plus for MongoDB

For a list of all messages, see IBM Knowledge Centre here.

# **Appendix A. Search guidelines**

Use filters to search for an entity such as a file or a restore point.

You can enter a character string to find objects with a name that exactly matches the character string. For example, searching for the term string.txt returns the exact match, string.txt.

Regular expression search entries are also supported. For more information, see <u>Search Text with Regular</u> Expressions.

You can also include the following special characters in the search. You must use a backslash (\) escape character before any of the special characters:

```
+ - & | ! ( ) { } [ ] ^ " ~ * ? : \
```

For example, to search for the file string[2].txt, enter the string[2].txt.

# Searching with wildcards

You can position wildcards at the beginning, middle, or end of a string, and combine them within a string.

# Match a character string with an asterisk

The following examples show search text with an asterisk:

- string\* searches for terms like string, strings, or stringency
- str\*ing searches for terms like string, straying, or straightening
- \*string searches for terms like string or shoestring

You can use multiple asterisk wildcards in a single text string, but multiple wildcards might considerably slow down a large search.

#### Match a single character with a question mark:

The following examples show search text with a question mark:

- string? searches for terms like strings, stringy, or string1
- st??ring searches for terms like starring or steering
- ???string searches for terms like hamstring or bowstring

# Appendix B. Accessibility features for the IBM Spectrum Protect product family

Accessibility features assist users who have a disability, such as restricted mobility or limited vision, to use information technology content successfully.

#### **Overview**

The IBM Spectrum Protect family of products includes the following major accessibility features:

- · Keyboard-only operation
- · Operations that use a screen reader

The IBM Spectrum Protect family of products uses the latest W3C Standard, WAI-ARIA 1.0 (www.w3.org/TR/wai-aria/), to ensure compliance with US Section 508 (www.access-board.gov/guidelines-and-standards/communications-and-it/about-the-section-508-standards/section-508-standards) and Web Content Accessibility Guidelines (WCAG) 2.0 (www.w3.org/TR/WCAG20/). To take advantage of accessibility features, use the latest release of your screen reader and the latest web browser that is supported by the product.

The product documentation in IBM Knowledge Center is enabled for accessibility. The accessibility features of IBM Knowledge Center are described in the <u>Accessibility section of the IBM Knowledge Center</u> help (www.ibm.com/support/knowledgecenter/about/releasenotes.html?view=kc#accessibility).

# **Keyboard navigation**

This product uses standard navigation keys.

# **Interface information**

User interfaces do not have content that flashes 2 - 55 times per second.

Web user interfaces rely on cascading style sheets to render content properly and to provide a usable experience. The application provides an equivalent way for low-vision users to use system display settings, including high-contrast mode. You can control font size by using the device or web browser settings.

Web user interfaces include WAI-ARIA navigational landmarks that you can use to quickly navigate to functional areas in the application.

#### Vendor software

The IBM Spectrum Protect product family includes certain vendor software that is not covered under the IBM license agreement. IBM makes no representation about the accessibility features of these products. Contact the vendor for accessibility information about its products.

# **Related accessibility information**

In addition to standard IBM help desk and support websites, IBM has a TTY telephone service for use by deaf or hard of hearing customers to access sales and support services:

TTY service 800-IBM-3383 (800-426-3383) (within North America)

For more information about the commitment that IBM has to accessibility, see  $\underline{\text{IBM Accessibility}}$  (www.ibm.com/able).

# **Notices**

This information was developed for products and services offered in the US. This material might be available from IBM in other languages. However, you may be required to own a copy of the product or product version in that language in order to access it.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data discussed herein is presented as derived under specific operating conditions. Actual results may vary.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

# COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows: © (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. \_enter the year or years\_.

# **Trademarks**

IBM, the IBM logo, and ibm.com® are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Adobe is a registered trademark of Adobe Systems Incorporated in the United States, and/or other countries.

Linear Tape-Open, LTO, and Ultrium are trademarks of HP, IBM Corp. and Quantum in the U.S. and other countries.

Intel and Itanium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, and Windows NT are trademarks of Microsoft Corporation in the United States, other countries, or both.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

UNIX is a registered trademark of The Open Group in the United States and other countries.

VMware, VMware vCenter Server, and VMware vSphere are registered trademarks or trademarks of VMware, Inc. or its subsidiaries in the United States and/or other jurisdictions.

# Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

### **Applicability**

These terms and conditions are in addition to any terms of use for the IBM website.

#### Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

#### Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

# **Rights**

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

# **Privacy policy considerations**

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information about this offering's use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <a href="http://www.ibm.com/privacy">http://www.ibm.com/privacy</a> and IBM's Online Privacy Statement at <a href="http://www.ibm.com/privacy/details">http://www.ibm.com/privacy/details</a> in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <a href="http://www.ibm.com/software/info/product-privacy">http://www.ibm.com/software/info/product-privacy</a>.

# Glossary

A glossary is available with terms and definitions for the IBM Spectrum Protect family of products. See the IBM Spectrum Protect glossary.

# Index

A	cloud provider (continued)
	editing <u>242</u>
Access control	cloud server
MongoDB 183	adding a Microsoft azure cloud resource 240
accessibility features <u>295</u>	adding an amazon s3 cloud resource 237
Add Db2 partitions <u>132</u>	adding an IBM Cloud Object Storage resource 238
adding	adding an s3 compatible cloud resource 241
Hyper-V servers <u>115</u>	creating
identities <u>285</u>	reports <u>272</u>
LDAP server <u>252</u>	resource groups <u>276</u>
Oracle application servers 216	roles <u>280</u>
sites 249	SLA policies <u>87</u>
SMTP server 253	users
SQL Server application servers 205	individual <u>283</u>
vCenter Server instances 93	LDAP group 283
virtual disks to a vCenter virtual machine 261	VADP proxies 103
vSnap servers 54	
Adding Db2 132	D
Adding MongoDB 185	
Administrative Console, logging on to 257	Db2
application server	system requirements 29
Db2 129	Db2 log backup 141
<del></del>	deleting
B	identities 285
В	LDAP server 254
Racking up	<del></del>
Backing up Db2 136	resource groups 279
	roles 283
backup	sites 251
jobs	SLA demo 91
on demand 234	SLA policies 91
backup jobs	SMTP server 254
ad hoc	users 284
on demand <u>234</u>	Detecting
creating	Db2 <u>134</u>
Hyper-V <u>117</u>	disability 295
IBM Spectrum Protect Plus 227	
Oracle <u>218</u>	E
SQL Server 207	
VMware 97	early availability updates, obtaining and applying 86
excluding VMDKs from <u>101</u>	editing
rerunning	identities 285
on demand <u>233</u>	LDAP server 254
starting	resource groups 278
on demand <u>232</u>	roles 282
on schedule <u>87</u>	settings 254
backup policies, <i>See</i> SLA policies	sites 250
Beta program	SLA policies 91
advantages <u>xi</u>	SMTP server 254
overview <u>xi</u>	users 284
	efix 86
C	Exchange Server
	system requirements 26
certificate	2
adding 246	-
deleting 246	F
cloud provider	formed naturally greating 112
deleting 242	fenced network, creating 112

files	K
restoring <u>126</u>	
searching for <u>293</u>	key
Finding Db2 <u>134</u>	adding <u>245</u> , <u>246</u>
firewalls 47	deleting 246, 248
<del>_</del>	keyboard 295
	keys 245
G	Knowledge Center vii
	Thiomsage contor <u>th</u>
global preferences	
managing <u>255</u>	L
H	LDAP
п	group, creating a user account for 283
Hyper V	server
Hyper-V	adding 252
adding 115	deleting 254
backup job, creating <u>117</u>	settings, editing 254
installing on virtual appliance <u>44</u>	Linux-based vCenter virtual appliance, backing up 102
restore job, creating <u>121</u>	
servers	Log archiving
detecting resources for <u>117</u>	Db2 <u>141</u>
enabling WinRM 116	logs
testing connection to 117	audit
virtual appliance	downloading <u>273</u>
accessing 259	viewing <u>273</u>
3.000008 <u>=0 &gt;</u>	system
	downloading 273, 289
I	viewing 273, 289
	<u> </u>
IBM Knowledge Center <u>vii</u>	
IBM spectrum protect server	M
adding a repository server 243	
identities	message
adding 285	prefixes <u>291</u>
deleting 285	messages 291
editing 285	MongoDB
installing	system requirements 32
download packages, obtaining 42	MongoDB application server 182
virtual appliance	<u> </u>
on Hyper-V 44	M
	N
on VMware <u>43</u>	make and a
vSnap servers	network
Hyper-V environment <u>53</u>	testing 260, 261
physical environment <u>51</u>	New in IBM Spectrum Protect Plus Version Version 10.1.4 $ix$
VMware environment <u>52</u>	
iSCSI utilities	0
installing 49	
	offline updates 81
1	Offload
J	IBM Spectrum Protect Server 243
ioho	online updates 81
jobs	•
backing up single resource 234	Oracle
canceling <u>233</u>	application servers
names of 231	adding <u>216</u>
pausing <u>233</u>	detecting resources for <u>217</u>
releasing <u>233</u>	testing connection to <u>218</u>
rerunning <u>233</u>	backup job, creating <u>218</u>
starting	multithreaded databases <u>216</u>
on demand 232	restore job, creating 220
on schedule 87	system requirements 34
types of 231	· —
Jobs and Operations 231	D.
<u></u>	P
	nvofovonoso
	preferences
	global

preferences (continued)	S
global <i>(continued)</i>	
managing <u>255</u>	Schedule 231
prerequisites	Schedule jobs
Db2 129	Backup 138, 154, 190
MongoDB 182	scripts for backup and restore operations
Prerequisites	uploading 235
MongoDB 183	service level agreement, See SLA policies
publications vii	Setting Db2
	SLA options 140
	sites
Q	adding 249
quial atant 67	deleting 251
quick start <u>67</u>	editing 250
	throttling 249, 250
R	SLA 138, 154, 190
	SLA options
RBAC	Db2 140
MongoDB <u>183</u>	SLA policies
reports	adding 87
custom, creating <u>272</u>	deleting 91
running	editing 91
on demand 271	SMTP
on schedule 272	
types of	server adding 253
backup storage utilization 267	
protection 268	deleting 254
system 269	settings, editing 254
VM environment 270	sponsor user program
repository server provider	advantages <u>xi</u>
deleting 245	overview <u>xi</u>
editing 244	SQL Server
rerunning	application servers
jobs	adding 205
on demand 233	detecting resources for 207
resource groups	testing connection to 207
creating 276	backup job, creating <u>207</u>
deleting 279	requirements for data protection 205
editing 278	restore job, creating 210
types of 277	system requirements 38
restore jobs	SSL certificate, uploading
creating	from administrative console <u>258</u>
Hyper-V 121	starting
IBM Spectrum Protect Plus 227	IBM Spectrum Protect Plus <u>69</u>
Oracle 220	jobs
SQL Server 210	on demand <u>232</u>
VMware 106	on schedule <u>87</u>
running	system requirements
Hyper-V 121	components <u>11</u>
Oracle 220	Db2 <u>29</u>
SQL Server 210	Exchange Server <u>26</u>
VMware 106	file index and restore 22
restore points, deleting 229	hypervisors <u>21</u>
	MongoDB 32
restore points, managing <u>228</u>	Oracle <u>34</u>
Restoring	SQL Server 38
Db2 142, 146, 148	system(
Restoring Db2	logs 273
Alternate instance 148	
Original instance <u>146</u>	Т
roles	1
creating 280	Testing connection
deleting 283	Db2 135
editing 282	time zone, setting 257
permission types 281	5 20110, 00ttill <u>207</u>

U
user access 5, 275 users  deleting 284 editing 284 individual, creating 283 LDAP group, creating 283 resource groups creating 276 deleting 279 editing 278 types of 277 roles creating 280 deleting 283 editing 282 permission types 281
V
VADP proxies  creating 103 options, setting 105 uninstalling 106 updating 84 virtual appliance accessing in Hyper-V 259 in VMware 259 adding a disk to 261 adding storage capacity 262 installing on Hyper-V 44 on VMware 43
Virtual appliance
updating <u>81</u> VMware
backup job, creating 97 backup job, excluding VMDKs from SLA policy 101 installing on virtual appliance 43 restore job creating a fenced network 112 restore job, creating 106 vCenter Server instances adding 93 vCenter Server, detecting resources 97 vCenter Server, testing connection to 97 virtual appliance
accessing <u>259</u>
virtual machine privileges, required <u>94</u> vSnap
updating 84 vSnap server administering network administration 63 storage administration 61 change throughput 59 deleting 55 editing 55 initializing advanced 57 simple 57
replication partnership, establishing <u>59</u>

```
vSnap server (continued)
storage options, managing <u>58</u>
storage pools, expanding <u>58</u>
vSnap servers
adding <u>54</u>
installing
Hyper-V environment <u>53</u>
physical environment <u>51</u>
VMware environment <u>52</u>
uninstalling <u>64</u>
```

# W

WinRM, enabling for connection to Hyper-V servers <u>116</u>

# IBW.

Product Number: 5737-F11

Printed in USA