

# **User Manual**

Software Version 7.1



Microsoft® Windows®XP Windows®2000 Windows NT®





### © 1996-2012 DeviceLock, Inc. All rights reserved.

Information in this document is subject to change without notice. No part of this document may be reproduced or transmitted in any form or by any means for any purpose other than the purchaser's personal use without the prior written permission of DeviceLock, Inc.

### Trademarks

DeviceLock and the DeviceLock logo are registered trademarks of DeviceLock, Inc. All other product names, service marks, and trademarks mentioned herein are trademarks of their respective owners.

DeviceLock - User Manual Software Version: 7.1 Updated: February 10, 2012

## Contents

ABOUT THIS MANUAL	6
CONVENTIONS	. 6
OVERVIEW	. 7
GENERAL INFORMATION	. 7
MANAGED ACCESS CONTROL FOR DEVICES AND PROTOCOLS	11
UNDERSTANDING DEVICELOCK CONTENT SECURITY SERVER HOW SEARCH SERVER WORKS	16 16
EXTENDING DEVICELOCK FUNCTIONALITY WITH CONTENTLOCK AND NETWORKLOCKLICENSING	18 22
RECOMMENDED BASIC SECURITY MEASURES	22
INSTALLATION	24
REQUIREMENTS	24
DEPLOYING DEVICELOCK SERVICE INTERACTIVE INSTALLATION UNATTENDED INSTALLATION INSTALLATION VIA MICROSOFT SYSTEMS MANAGEMENT SERVER REMOTE INSTALLATION VIA DEVICELOCK MANAGEMENT CONSOLE REMOTE INSTALLATION VIA DEVICELOCK ENTERPRISE MANAGER INSTALLATION VIA GROUP POLICY	24 24 31 32 33 34 35
INSTALLING MANAGEMENT CONSOLES	43
INSTALLING DEVICELOCK ENTERPRISE SERVER PLANNING INFRASTRUCTURE INTERACTIVE INSTALLATION	50 51 51
INSTALLING DEVICELOCK CONTENT SECURITY SERVER	68
DEVICELOCK CERTIFICATES	77
OVERVIEW	77
GENERATING DEVICELOCK CERTIFICATES	77
INSTALLING/REMOVING DEVICELOCK CERTIFICATE	79
DEVICELOCK SIGNING TOOL	84
OVERVIEW	84
DEVICE CODE	84
SERVICE SETTINGS	86
DEVICELOCK MANAGEMENT CONSOLE	90
OVERVIEW	90
INTERFACE	92
CONNECTING TO COMPUTERS	93

POSSIBLE CONNECTION ERRORS	96
MANAGING DEVICELOCK SERVICE	97 99 122
PERMISSIONS (REGULAR PROFILE)	
AUDITING & SHADOWING (REGULAR PROFILE)	
USB DEVICES WHITE LIST (REGULAR PROFILE)	
MEDIA WHITE LIST (REGULAR PROFILE)	148 152
AUDIT LOG VIEWER (SERVICE)	
SHADOW LOG VIEWER (SERVICE)	159
MANAGING DEVICELOCK ENTERPRISE SERVER	
SERVER OPTIONS	
AUDIT LOG VIEWER (SERVER)	168 172
SERVER LOG VIEWER	
MONITORING	178
MANAGING AND USING DEVICELOCK CONTENT SECURITY SERVER	
NAVIGATING DEVICELOCK CONTENT SECURITY SERVER	
SERVER	
CONFIGURING FULL-TEXT SEARCH SETTINGS FOR SEARCH SERVER	
USING SEARCH SERVER	207
DEVICELOCK GROUP POLICY MANAGER	218
OVERVIEW	218
OVERVIEW APPLYING GROUP POLICY	218 219
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES	218 219 219
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER	218 219 219 220
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER USING DEVICELOCK GROUP POLICY MANAGER	218 219 219 220 224
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER USING DEVICELOCK GROUP POLICY MANAGER USING RESULTANT SET OF POLICY (RSOP)	218 219 219 220 224 227
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER USING DEVICELOCK GROUP POLICY MANAGER USING RESULTANT SET OF POLICY (RSOP) DEVICELOCK SERVICE SETTINGS EDITOR	218 219 220 220 224 227 230
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER USING DEVICELOCK GROUP POLICY MANAGER USING RESULTANT SET OF POLICY (RSOP) DEVICELOCK SERVICE SETTINGS EDITOR OVERVIEW	218 219 220 224 227 230 230
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER USING DEVICELOCK GROUP POLICY MANAGER USING RESULTANT SET OF POLICY (RSOP) DEVICELOCK SERVICE SETTINGS EDITOR OVERVIEW DEVICELOCK ENTERPRISE MANAGER	218 219 220 224 227 230 230 232
OVERVIEW	218 219 220 220 224 227 230 230 232
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER. USING DEVICELOCK GROUP POLICY MANAGER. USING RESULTANT SET OF POLICY (RSOP) DEVICELOCK SERVICE SETTINGS EDITOR OVERVIEW DEVICELOCK ENTERPRISE MANAGER OVERVIEW INTERFACE.	218 219 220 220 224 227 230 230 232 232 233
OVERVIEW	218 219 220 224 227 230 230 232 232 232 233 234
OVERVIEW	218 219 220 220 220 220 227 230 230 232 232 233 234 234 234
OVERVIEW	218 219 219 220 224 227 230 230 232 232 233 234 234 234 234 234 234 240 241
OVERVIEW	218 219 220 220 220 220 227 227 230 230 232 232 232 232 234 234 240 241 242
OVERVIEW	218 219 219 220 224 227 230 230 230 232 233 234 234 234 234 242 242 242 242
OVERVIEW APPLYING GROUP POLICY STANDARD GPO INHERITANCE RULES STARTING DEVICELOCK GROUP POLICY MANAGER. USING DEVICELOCK GROUP POLICY MANAGER. USING RESULTANT SET OF POLICY (RSOP) <b>DEVICELOCK SERVICE SETTINGS EDITOR</b> OVERVIEW <b>DEVICELOCK ENTERPRISE MANAGER</b> OVERVIEW INTERFACE. SCAN NETWORK DIALOG BOX SELECTING COMPUTERS SELECTING PLUG-INS. STARTING A SCAN PLUG-INS AUDIT LOG VIEWER INSTALL SERVICE	218 219 220 220 220 220 227 230 230 230 232 232 233 234 234 241 241 242 243 243
OVERVIEW	218 219 219 220 224 227 230 230 230 232 232 233 234 234 234 241 242 243 243 243 243 243 243 245

SET SERVICE SETTINGS SHADOW LOG VIEWER UNINSTALL SERVICE	246 247 247
OPEN / SAVE / EXPORT	248
COMPARING DATA	249
FILTERING DATA	253
CONTENT-AWARE RULES FOR DEVICES (REGULAR PROFILE)	256
CONTENT-AWARE RULES FOR ACCESS CONTROL OPERATIONS	256
CONTENT-AWARE RULES FOR SHADOW COPY OPERATIONS	260
CONFIGURING CONTENT DETECTION SETTINGS FILE TYPE DETECTION CONTENT GROUPS KEYWORDS CONTENT GROUPS PATTERN CONTENT GROUPS DOCUMENT PROPERTIES CONTENT GROUPS COMPLEX CONTENT GROUPS VIEWING BUILT-IN CONTENT GROUPS DUPLICATING BUILT-IN CONTENT GROUPS EDITING AND DELETING CUSTOM CONTENT GROUPS TESTING CONTENT GROUPS MANAGING CONTENT-AWARE RULES DEFINING CONTENT-AWARE RULES	261 262 265 270 274 278 281 282 282 283 284 284
EDITING CONTENT-AWARE RULES COPYING CONTENT-AWARE RULES EXPORTING AND IMPORTING CONTENT-AWARE RULES UNDEFINING CONTENT-AWARE RULES DELETING CONTENT-AWARE RULES	288 289 290 292 292
CONTENT-AWARE RULES FOR PROTOCOLS (REGULAR PROFILE)	294
CONTENT-AWARE RULES FOR ACCESS CONTROL OPERATIONS	294
CONTENT-AWARE RULES FOR SHADOW COPY OPERATIONS	296
CONFIGURING CONTENT DETECTION SETTINGS FILE TYPE DETECTION CONTENT GROUPS KEYWORDS CONTENT GROUPS PATTERN CONTENT GROUPS DOCUMENT PROPERTIES CONTENT GROUPS COMPLEX CONTENT GROUPS VIEWING BUILT-IN CONTENT GROUPS DUPLICATING BUILT-IN CONTENT GROUPS EDITING AND DELETING CUSTOM CONTENT GROUPS TESTING CONTENT GROUPS	298 298 301 306 310 313 316 317 318 319
MANAGING CONTENT-AWARE RULES DEFINING CONTENT-AWARE RULES EDITING CONTENT-AWARE RULES COPYING CONTENT-AWARE RULES EXPORTING AND IMPORTING CONTENT-AWARE RULES UNDEFINING CONTENT-AWARE RULES	319 320 323 324 326 328

PROTOCOLS (REGULAR PROFILE)	330
MANAGING PERMISSIONS FOR PROTOCOLS	. 331
SETTING AND EDITING PERMISSIONS	. 335
UNDEFINING PERMISSIONS	. 337
MANAGING AUDIT AND SHADOWING RULES FOR PROTOCOLS	. 338
DEFINING AND EDITING AUDIT AND SHADOWING RULES	. 346
UNDEFINING AUDIT AND SHADOWING RULES	. 348
MANAGING PROTOCOLS WHITE LIST.	.349
DEFINING PROTOCOLS WHITE LIST.	.353
EDITING PROTOCOLS WHITE LIST.	.356
COPYING RULES OF PROTOCOLS WHITE LIST	.357
EXPORTING AND IMPORTING PROTOCOLS WHITE LIST	.358
UNDEFINING PROTOCOLS WHITE LIST.	.360
DELETING RULES OF PROTOCOLS WHITE LIST	.361
MANAGING SECURITY SETTINGS FOR PROTOCOLS	. 362
DEFINING AND CHANGING SECURITY SETTINGS	. 363
UNDEFINING SECURITY SETTINGS	. 363
DEVICELOCK REPORTS	365
REPORT CATEGORIES AND TYPES	. 365
AUDIT LOG REPORTS	. 366
SHADOW LOG REPORTS	. 370
CONFIGURING E-MAIL DELIVERY OF REPORTS	. 372
SETTING DEFAULT FORMAT FOR REPORTS	. 374
DEFINING REPORT PARAMETERS	. 374
REPORT OPTIONS DIALOG BOX	. 375
MANAGING REPORTS RUNNING REPORTS REFRESHING REPORTS VIEWING REPORTS VIEWING REPORT PARAMETERS EXPORTING AND SAVING REPORTS SENDING REPORTS THROUGH E-MAIL DELETING REPORTS	. 380 . 380 . 381 . 382 . 382 . 383 . 383 . 384 . 384
DEVICELOCK SECURITY POLICIES (OFFLINE PROFILE)	386
CONFIGURING OFFLINE MODE DETECTION SETTINGS	. 387
SWITCHING BETWEEN ONLINE AND OFFLINE MODE	. 389
MANAGING OFFLINE SECURITY POLICIES FOR DEVICES	. 389
MANAGING OFFLINE PERMISSIONS	. 390
MANAGING OFFLINE AUDIT AND SHADOWING RULES	. 394
MANAGING OFFLINE USB DEVICES WHITE LIST	. 399
MANAGING OFFLINE MEDIA WHITE LIST	. 406
MANAGING OFFLINE CONTENT-AWARE RULES FOR DEVICES	. 412
MANAGING OFFLINE SECURITY SETTINGS	. 422
MANAGING OFFLINE SECURITY POLICIES FOR PROTOCOLS	.427
MANAGING OFFLINE PERMISSIONS FOR PROTOCOLS	.427

MANAGING OFFLINE AUDIT AND SHADOWING RULES FOR PROTOCOLS MANAGING OFFLINE PROTOCOLS WHITE LIST MANAGING OFFLINE CONTENT-AWARE RULES FOR PROTOCOLS MANAGING OFFLINE SECURITY SETTINGS FOR PROTOCOLS	432 436 446 457
TEMPORARY WHITE LIST	460
TEMPORARY WHITE LIST AUTHORIZATION TOOL	461
APPENDIX	464
PERMISSIONS AND AUDIT EXAMPLES FOR DEVICES PERMISSIONS EXAMPLES AUDIT & SHADOWING RULES EXAMPLES	464 464 475
PERMISSIONS EXAMPLES FOR PROTOCOLS	477
CONTENT-AWARE RULES EXAMPLES	

## **About This Manual**

This manual provides detailed information about how to install and use DeviceLock. It is primarily intended for administrators, security specialists, and other IT professionals who focus on how to provide data security within an organization.

This manual assumes some basic knowledge of the Microsoft Windows operating system and networking as well as the ability to create a local area network (LAN).

## Conventions

CONVENTION	DESCRIPTION
Bold text	Represents user interface elements such as menus and commands, dialog box titles and options.
Italic text	Used for comments.
<u>Blue text</u>	Represents hyperlinks.
Note	Used to provide supplementary information.
Caution	Used to alert you to possible problems.
<b>Best Practice</b>	Used to provide best practice recommendations.
Plus sign (+)	Used to indicate a combination of keys that you must press at the same time.

The following table lists the conventions used in this manual.

## **Overview**

## **General Information**

Preventing unauthorized downloading as well as the uploading of inappropriate software and data is important when trying to protect and administer a company's computer network. The traditional solution has been a physical lock on the floppy drive. DeviceLock eliminates the need for physical locks and has a number of advantages.

DeviceLock is easy to install. Administrators can have instant access from remote computers when necessary. The administrator of the machine or domain can designate user access to floppy drives, CD-ROM drives, other removable media, tape drives, WiFi, and Bluetooth adapters, or USB, FireWire, infrared, and serial and parallel ports. All types of file systems are supported.

NetworkLock, an extension to DeviceLock, provides control over network communications. Administrators can designate user access to the FTP, HTTP, SMTP, Telnet protocols, instant messengers (ICQ/AOL Instant Messenger, Windows Live Messenger and Windows Messenger, Jabber, IRC, Yahoo! Messenger, Mail.ru Agent), webmail and social networking applications (AOL Mail, Gmail, GMX Mail, Hotmail, Mail.ru, Rambler Mail, Web.de, Yahoo! Mail, and Yandex Mail; Facebook, Google+, LinkedIn, LiveJournal, MeinVZ, Myspace, Odnoklassniki, SchuelerVZ, StudiVZ, Tumblr, Twitter, Vkontakte, XING).

ContentLock, another extension to DeviceLock, extracts and filters the content of data copied to removable drives and plug-n-play storage devices, as well as that transmitted over the network. Administrators can create rules that specify which content can be copied and transmitted.

DeviceLock can audit user activity for a particular device type or protocol on a local computer. Based on the user's security context, this capability allows you to audit activities that belong to a certain user or user group. DeviceLock employs the standard event logging subsystem and writes audit records to the Windows event log.

DeviceLock supports data shadowing – the ability to mirror all data copied to external storage devices, transferred through serial and parallel ports or transmitted over the network. A full copy of the files can be saved into the SQL database. Shadowing, like auditing, can be defined on a per-user basis.

Moreover, the DeviceLock data shadowing function is compatible with the National Software Reference Library maintained by the National Institute of Standards and Technology (NIST) and with the Hashkeeper Database designed and maintained by U.S. DOJ National Drug Intelligence Center (NDIC).

The data logged by DeviceLock can be checked against hash databases (collections of digital signatures of known, traceable data) and used in computer forensics.

You may also create your own database with digital signatures (SHA-1, MD5 and CRC32 are supported) of critical files and then use it for tracing purposes. For example, you can trace which users are copying signatured files, at what time, and with which devices.

For information on how to use hash databases in cooperation with DeviceLock, please contact our technical support team.

More information about hash databases and their samples can be found at the National Software Reference Library's Web site: <u>http://www.nsrl.nist.gov</u>.

Also, DeviceLock provides instant searching of text across shadowed files and audit logs stored in the centralized database. DeviceLock can automatically recognize, index, search and display documents in many formats, such as: Adobe Acrobat (PDF), Ami Pro, Archives (GZIP, RAR, ZIP), Lotus 1-2-3, Microsoft Access, Microsoft Excel, Microsoft PowerPoint, Microsoft Word, Microsoft Works, OpenOffice (documents, spreadsheets and presentations), Quattro Pro, WordPerfect, WordStar and many others.

In addition to the standard (per computer) way of managing permissions, DeviceLock also provides you with a more powerful mechanism – permissions and settings can be changed and deployed via Group Policy in an Active Directory domain.

Tighter integration into the Active Directory is a very important function of DeviceLock. It makes DeviceLock's permissions management and deployment easier for large networks and more convenient for system administrators.

Integration into the Active Directory eliminates the need to install more third-party applications for centralized management and deployment. DeviceLock does not need to have its own server-based version to control the entire network, instead it uses standard functions provided by the Active Directory.

DeviceLock consists of three parts: the agent (DeviceLock Service), the server (DeviceLock Enterprise Server and DeviceLock Content Security Server) and the management console (DeviceLock Management Console, DeviceLock Group Policy Manager or DeviceLock Enterprise Manager).

1. DeviceLock Service is the core of DeviceLock. DeviceLock Service is installed on each client system, runs automatically, and provides device and network protection on the client machine while remaining invisible to that computer's local users.



2. DeviceLock Enterprise Server is an optional component for centralized collection and storage of the shadow data and audit logs. DeviceLock Enterprise Server uses MS SQL Server to store its data. You can install several DeviceLock Enterprise Servers to uniformly spread the network load.

#### Overview



DeviceLock Content Security Server is another optional component which includes Search Server for instant search of text within shadowed files and other logs stored on DeviceLock Enterprise Server. For more information, see "<u>Understanding</u> <u>DeviceLock Content Security Server</u>."

3. The management console is the control interface that systems administrators use to remotely manage each system that has DeviceLock Service. DeviceLock ships with three different management consoles: DeviceLock Management Console (the MMC snap-in), DeviceLock Enterprise Manager and DeviceLock Group Policy Manager (integrates into the Windows Group Policy Editor). DeviceLock Management Console is also used to manage DeviceLock Enterprise Server and DeviceLock Content Security Server.



## **Managed Access Control for Devices and Protocols**

Access control for devices works in the following way: Every time the user wants to access a device, DeviceLock intercepts this request at the kernel level of the OS. Depending on the device's type and the connection interface (e.g. USB), DeviceLock checks the user rights in the appropriate Access Control List (ACL). If the user does not have the right to access this device, an "access denied" error is returned.

Access checking can occur at three levels: the interface (port) level, the type level and the file content level. Some devices are checked at all three levels, while others only at one level – either interface (port) or type.



Consider the case of a user connecting a USB flash drive to the USB port. Here DeviceLock would first check whether the USB port is open or locked at the interface level. Next, because Windows recognizes a USB flash drive as a removable storage device, DeviceLock will also check permissions at the type level (Removable). Finally, DeviceLock will also check permissions at the file content level (Content-Aware Rules). In contrast, a USB scanner would only be checked at the interface level (USB port), as DeviceLock doesn't distinguish scanners at the type level.



There are additional <u>Security Settings</u> that can turn off access control for classes of devices (for example, all USB printers) while others remain under control. In the case of a device belonging to a class for which control is disabled, DeviceLock allows all requests to connect this device at the interface (port) level.

Also, DeviceLock supports the <u>white listing</u> of specific devices; in other words, you can turn off access control for only specific devices (for example, certain USB printer).

**Note:** If access to a device is denied at the interface (port) level, DeviceLock does not check permissions at the type level. However, if access is granted at the interface (port) level,

DeviceLock also checks permissions at the type level. Only when access is granted at both levels, the user can connect the device.

Access control for protocols works in the following way: Every time the user wants to access a remote network resource, DeviceLock intercepts this connection request at the kernel level of the OS and checks the user rights in the appropriate Access Control List (ACL). If the user does not have the right to access this protocol, an "access denied" error is returned.

**Note:** Access control settings for Social Networks and Web Mail override access control settings for HTTP. For example, if users are allowed to access Gmail, but disallowed to use HTTP, they nevertheless can access the service.

Access checking can occur at two levels: the protocol level and the data content level. All network connections except for Telnet connections are checked at both levels.

Consider the case of a user connecting to a social networking site. Here DeviceLock would first check whether Social Networks are open or locked at the protocol level. Next, DeviceLock will also check permissions at the data content level (Content-Aware Rules).



Also, DeviceLock supports the <u>white listing</u> of protocols. With the Protocols White List, you can turn off access control for connections with specific parameters (for example, HTTP connections to specific hosts and ports).

### Understanding DeviceLock Content Security Server

DeviceLock Content Security Server is a new optional component of DeviceLock. It includes Search Server which provides full-text searching of logged data stored on DeviceLock Enterprise Server. These search capabilities make it easier and more efficient to manage the increasing amount of data in DeviceLock Enterprise Server databases.

DeviceLock Content Security Server includes the following features:

- **Full-text search capability support**. Through the use of Search Server, DeviceLock Content Security Server allows you to instantly search for relevant text data based on various search criteria.
- **Flexible configuration options**. There is support for many different configuration options, enabling you to optimize the performance of DeviceLock Content Security Server for your unique installation.

You can use full-text searches to find data that you cannot find by filtering data in the log viewers. The full-text search functionality is especially useful in situations when you need to search for shadow copies of documents based on their contents.

### Use Case – Preventing leaks of confidential information

Security specialists who are tasked with keeping sensitive information confidential can regularly use Search Server to easily find, retrieve and analyze all shadow copies of files containing specific business-critical data, for example, customers or price lists. The log records associated with found shadow copies will help to determine when and by whom confidential information was copied. With this information, security specialists can take immediate steps to avoid possible information disclosure and distribution outside the company.

You can configure and use DeviceLock Content Security Server by using DeviceLock Management Console.

### **How Search Server Works**

Search Server performs the following functions:

- Indexes DeviceLock Enterprise Server data.
- Executes full-text queries after the data has been indexed.

These functions are described in more detail below.

#### Indexing DeviceLock Enterprise Server Data

Indexing is a process through which the textual data on DeviceLock Enterprise Server becomes searchable and retrievable. Search Server starts the indexing process automatically as soon as you specify DeviceLock Enterprise Server(s). The indexing process can result in either the creation or update of the full-text index. There is only one full-text index per Search Server, making management more efficient. The full-text index stores information about significant words and their location. During index creation or update, Search Server discards noise words (such as prepositions, articles, and so on) that do not help the search.

Search Server indexes all text data from the following content sources: Audit Log, Shadow Log, Deleted Shadow Data Log, Server Log, and Monitoring Log.

The indexing process happens in two stages. In the first stage, Search Server extracts significant words from shadow copies and log records and saves them to temporary indexes for each specified DeviceLock Enterprise Server. For each temporary index, Search Server processes 1,000 records from each log.

In the second stage, when either the number of temporary indexes becomes equal to 50 or 10 minutes pass, all temporary indexes are combined into a permanent master index that is used for search queries. The process of combining temporary indexes into a master index is called *merging*.

The creation of the master index is a time-intensive process. Indexing speed can vary considerably depending on the type of data being indexed and the hardware being used. Generally, indexing speed is between 30 and 120 MB/minute. Consider the following example:

- Data: 170 GB, consisting of 4,373,004 mixed-type files (HTML, office documents, text)
- Indexing time: 24.7 hours (6.8 GB/hour)
- Index size: 12% of original document size
- Hardware: Pentium® 4 Processor 550 (3.40GHz, 800 FSB), 2GB RAM, internal SATA RAID-0 drives

### Executing Full-Text Queries

After the DeviceLock Enterprise Server data has been indexed, you can run full-text queries. These queries can search for one or more specific words or phrases.

When a search query is executed, Search Server processes the query and retrieves a list of results from the index that matches the criteria of the query. Filtering can be applied to the search to narrow the result set returned. For example, the results can be filtered by log or date.

Querying the full-text index is extremely fast and flexible. A search operation takes only seconds to locate and return matches for particular search criteria. For detailed information about the search results page and search results, see "Working with Search Results."

### Extending DeviceLock Functionality with ContentLock and NetworkLock

DeviceLock comes with ContentLock and NetworkLock - separately licensed components that provide additional functionality for DeviceLock. These components are installed automatically but require a license to function. For more information on ContentLock and NetworkLock licenses, see "Licensing."

NetworkLock adds comprehensive context control capabilities over endpoint network communications. It supports port-independent network protocol and application detection and selective blocking, message and session reconstruction with file, data, and parameter extraction, as well as event logging and data shadowing. NetworkLock controls most popular network protocols and applications such as: plain and SSL-protected SMTP email communications (with messages and attachments controlled separately), Web access and other HTTP-based applications including content inspection of encrypted HTTPS sessions (specifically, webmail and social networking applications like Gmail, Yahoo! Mail, Windows Live Mail, Facebook, Twitter, LiveJournal, etc.), instant messengers (ICQ/AOL, MSN Messenger, Jabber, IRC, Yahoo! Messenger, Mail.ru Agent), file transfers over FTP and FTP-SSL protocols, as well as telnet sessions.

NetworkLock is represented in the user interface of DeviceLock Management Console, Service Settings Editor and DeviceLock Group Policy Manager by the **Protocols** node.



NetworkLock includes the following key features and benefits:

- Protocol access control. You can control which users or groups can gain access to the FTP, HTTP, SMTP, Telnet protocols, instant messengers (ICQ/AOL Instant Messenger, Windows Live Messenger and Windows Messenger, Jabber, IRC, Yahoo! Messenger, Mail.ru Agent), as well as webmail and social networking applications (AOL Mail, Gmail, GMX Mail, Hotmail, Mail.ru, Rambler Mail, Web.de, Yahoo! Mail, Yandex Mail; Facebook, Google+, LinkedIn, LiveJournal, MeinVZ, Myspace, Odnoklassniki, SchuelerVZ, StudiVZ, Tumblr, Twitter, Vkontakte, XING) depending on the time of day and day of the week.
- Protocols White List. Lets you selectively allow network communication over specified protocols regardless of existing protocol blocking settings. The white list is most effective in "least privilege" scenarios when you block all

protocol traffic and then specifically authorize only what is required for employees to perform their daily job duties.

• **Content-Aware Rules (File Type Detection)**. You can selectively allow or deny access to specific types of files transmitted over the network. Recognition and identification of file types is based solely upon the content of files. This efficient and reliable algorithm allows for correct identification and handling of files regardless of the file extension. You can also use Content-Aware Rules to allow or deny shadow copying of specific file types.

**Note:** You must purchase a ContentLock license to gain access to enhanced capabilities of the Content-Aware Rules feature.

• **Audit and shadowing**. Allows you to track user activity for specified protocols and log a full copy of data/files transmitted over the network.

ContentLock is a content monitoring and filtering component that greatly enhances the capabilities of the Content-Aware Rules feature. With ContentLock, you can not only grant or deny access to information based on real file types but also create regular expressions patterns with numerical conditions and Boolean combinations of matching criteria and keywords. Recognizing more than eighty file formats and data types, ContentLock extracts and filters the content of data copied to removable drives and plug-n-play storage devices, as well as that transmitted over the network. With ContentLock, you can also filter shadowed data down to just those pieces of information meaningful to security auditing, incident investigations and forensic analysis before saving in the Shadow Log. This tremendously reduces storage space and network bandwidth requirements for shadow log delivery to the central database.

ContentLock includes the following key features and benefits:

- **Content-based document access control**. You can control access to documents depending on their content. Thus, you can block sensitive content leakage while allowing authorized employees to gain access to the information they need to collaborate.
- **Content-based filtering of shadow data**. You can specify that only data that contains sensitive information is shadow copied and saved to the Shadow Log, thus reducing the volume of unnecessary log data and making the log files easier to work with.
- Expansive coverage of multiple file formats and data types. You can protect content for the following file formats and data types: Adobe Acrobat (.pdf), Adobe Framemaker MIF (.mif), Ami Pro (.sam), Ansi Text (.txt), SCII Text, ASF media files (metadata only) (.asf), CSV (Comma-separated values) (.csv), DBF (.dbf), EBCDIC, EML files (emails saved by Outlook Express) (.eml), Enhanced Metafile Format (.emf), Eudora MBX message files (.mbx), Flash (.swf), GZIP (.gz), HTML (.htm, .html), JPEG (.jpg), Lotus 1-2-3 (.123, .wk?), MBOX email archives (including Thunderbird) (.mbx), MHT archives

(HTML archives saved by Internet Explorer) (.mht), MIME messages, MSG files (emails saved by Outlook) (.msg), Microsoft Access MDB files (.mdb, .accdb, including Access 2007 and Access 2010), Microsoft Document Imaging (.mdi), Microsoft Excel (.xls), Microsoft Excel 2003 XML (.xml), Microsoft Excel 2007 and 2010 (.xlsx), Microsoft Outlook/Exchange Messages, Notes, Contacts, Appointments, and Tasks, Microsoft Outlook Express 5 and 6 (.dbx) message stores, Microsoft PowerPoint (.ppt), Microsoft PowerPoint 2007 and 2010 (.pptx), Microsoft Rich Text Format (.rtf), Microsoft Searchable Tiff (.tiff), Microsoft Word for DOS (.doc), Microsoft Word for Windows (.doc), Microsoft Word 2003 XML (.xml), Microsoft Word 2007 and 2010 (.docx), Microsoft Works (.wks), MP3 (metadata only) (.mp3), Multimate Advantage II (.dox), Multimate version 4 (.doc), OpenOffice versions 1, 2, and 3 documents, spreadsheets, and presentations (.sxc, .sxd, .sxi, .sxw, .sxg, .stc, .sti, .stw, .stm, .odt, .ott, .odq, .otq, .odp, .otp, .ods, .ots, .odf) (includes OASIS Open Document Format for Office Applications), Quattro Pro (.wb1, .wb2, .wb3, .qpw), QuickTime (.mov, .m4a, .m4v), TAR (.tar), TIFF (.tif), TNEF (winmail.dat files), Treepad HJT files (.hjt), Unicode (UCS16, Mac or Windows byte order, or UTF-8), Visio XML files (.vdx), Windows Metafile Format (.wmf), WMA media files (metadata only) (.wma), WMV video files (metadata only) (.wmv), WordPerfect 4.2 (.wpd, .wpf), WordPerfect (5.0 and later) (.wpd, .wpf), WordStar version 1, 2, 3 (.ws), WordStar versions 4, 5, 6 (.ws), WordStar 2000, Write (.wri), XBase (including FoxPro, dBase, and other XBase-compatible formats) (.dbf), XML (.xml), XML Paper Specification (.xps), XSL, XyWrite, ZIP (.zip).

- Automated protection of new documents. You can automatically apply content-based security policies to new documents as they are created.
- **Multiple content detection methods**. You can use multiple methods to identify sensitive content contained in documents (based on regular expressions, keywords, and document properties).
- **Centralized content management**. Content-Aware Rules are created based on content groups that enable you to centrally define types of content for which you want to control access.
- Ability to override device type/protocol-level policies. You can selectively allow or deny access to certain content regardless of preset permissions at the device type-/protocol-level.
- Inspection of files within archives. Allows you to perform deep inspection
  of each individual file contained in an archive. The following inspection
  algorithm is used: When a user attempts to copy an archive file to a device or
  transmit it over the network, all files are extracted from the archive and
  analyzed separately to detect the content to which access is denied by
  Content-Aware Rules. If Content-Aware Rules deny access to at least one of
  the files extracted from the archive, the user is denied access to the archive.
  If Content-Aware Rules allow access to all of the files extracted from the
  archive, the user is allowed access to the archive. All archived files are

extracted to the Temp folder of the System user. Typically, the system Temp folder resides in the following location: %windir%\Temp directory. If DeviceLock Service has no access to the Temp folder, the archived files are not analyzed and access to the archive is denied only if any one of the following conditions is true:

- There is a Deny Content-Aware Rule
- Permissions set for the device type or protocol deny access

All nested archives are also unpacked and analyzed one by one. Archive files are detected by content, not by extension. The following archive formats are supported: 7z (.7z); ZIP (.zip); GZIP (.gz, .gzip, .tgz); BZIP2 (.bz2, .bzip2, .tbz2, .tbz); TAR (.tar); LZMA (.lzma); RAR (.rar); CAB (.cab); ARJ (.arj); Z (.z, .taz); CPIO (.cpio); RPM (.rpm); DEB (.deb); LZH (.lzh, .lha); CHM (.chm, .chw, .hxs); ISO (.Iso); UDF (.Iso); COMPOUND (.Msi); WIM (.wim, .swm); DMG (.dmg); XAR (.xar); HFS (.hfs); NSIS (.exe). Split (or multi-volume) and password-protected archives are not unpacked.

- Text in picture detection. The use of the text in picture detection technology allows you to classify all images into two groups: text images (images that contain text, for example, scanned documents, screen shots of documents) and non-text images (images that do not contain text) and separately control access to each group. For example, you can allow certain users to copy non-text images to devices, but prevent them from writing text images thus preventing leakage of sensitive information within image files. The following image files are supported: BMP files; Dr. Halo CUT files; DDS files; EXR files; Raw Fax G3 files; GIF files; HDR files; ICO files; IFF files (except Maya IFF files); JBIG; JNG files; JPEG/JIF files; JPEG-2000 File Format; JPEG-2000 codestream; KOALA files; Kodak PhotoCD files; MNG files; PCX files; PBM/PGM/PPM files; PFM files; Sun RAS files; SGI files; TARGA files; TIFF files; WBMP files; XBM files; XPM files.
- **Inspection of images embedded in documents**. Allows you to perform deep inspection of each individual image embedded in Adobe Portable Document Format (PDF) files, Rich Text Format (RTF) and Microsoft Office documents (.doc, .xls, .ppt, .docx, .xlsx, .pptx). All embedded images are extracted from these documents to the Temp folder of the System user and analyzed independently from text to detect the content to which access is denied by Content-Aware Rules. The text contained inside documents is checked by Content-Aware Rules that are created based on Keywords, Pattern or Complex content groups. Embedded images are checked by Content-Aware Rules that are created based on File Type Detection, Document Properties or Complex content groups. Access to documents is granted only when Content-Aware Rules allow access to text and all of the images contained in documents.

### Licensing

If you want to use the capabilities of NetworkLock and ContentLock, you must purchase NetworkLock and ContentLock licenses in addition to basic DeviceLock licenses. A NetworkLock license enables you to use the Protocols feature. A ContentLock license enables you to create and use Content-Aware Rules based on regular expressions, keywords, and document properties as well as complex rules based on Boolean combinations of matching criteria.

If you use different types of licenses, consider the following:

- If you have a basic DeviceLock license, a ContentLock license, and a NetworkLock license, you can use the Protocols feature, create and use Content-Aware Rules based on file types, regular expressions, keywords, and document properties as well as complex rules.
- If you have only a basic DeviceLock license, you cannot use the Protocols feature, and you cannot create and use Content-Aware Rules based on regular expressions, keywords, and document properties as well as complex rules. You can create and use Content-Aware Rules based on file types (File Type Detection).
- If you have a basic DeviceLock license and a ContentLock license, you can create and use Content-Aware Rules based on file types, regular expressions, keywords, and document properties as well as complex rules. You cannot use the Protocols feature.
- If you have a basic DeviceLock license and NetworkLock license, you can use the Protocols feature and create and use Content-Aware Rules based on file types. You cannot create and use Content-Aware Rules based on regular expressions, keywords, and document properties as well as complex rules.
- A basic DeviceLock license is obligatory, while NetworkLock and ContentLock licenses are optional. If a basic license is missing or invalid, DeviceLock runs in a trial mode only. The number of NetworkLock and/or ContentLock licenses must equal or exceed the number of basic DeviceLock licenses.
- The trial period for ContentLock and NetworkLock is 30 days.

### **Recommended Basic Security Measures**

Following is a series of basic security rules that should be met for computers that you want to install in a corporate network:

• **Change the boot sequence**. The hard disk must be the first boot device. Change the boot sequence in the BIOS so that the computer does not boot from the floppy, USB drive or CD-ROM. If the hard disk is not the first boot device, someone can use a bootable CD or USB Flash Drive to directly access the hard disk drive.

- **Protect the BIOS with a password**. The password should be set to the BIOS so only an authorized person can make changes there. If the BIOS is not password protected, someone can change the boot sequence and use a bootable CD, floppy or USB Flash Drive (see above).
- **Seal computer cases and chassis**. Protect the hardware with a seal. Otherwise, it is possible to plug an external boot device directly to the computer and access the hard disk. Moreover, if someone can physically access the motherboard, it is very easy to locate the CMOS reset jumper and clear the BIOS password (see above).
- **Do not give Administrative rights to regular users**. Regular local users should not be members of the local Administrators group. It is not a good practice to grant users administrative rights to their computers. *However, if for some reason users on your network have administrator privileges on their local computers, DeviceLock provides another level of protection. No one except authorized DeviceLock administrators can connect to, stop, or uninstall DeviceLock Service. Even members of the local Administrators group cannot disable DeviceLock if they are not in the list of the authorized DeviceLock administrators.*
- **Remove the Recovery Console**. If the Windows Recovery Console is installed on the local computer, someone can boot to the recovery mode and workaround any number of security measures including disabling DeviceLock Service (however, this requires the local administrator password). For this reason, we recommend deleting the Recovery Console. For more information on how to install, remove and use the Recovery Console, please refer to the Microsoft's on-line article:

http://support.microsoft.com/default.aspx?scid=kb;en-us;307654.

## Installation

### Requirements

DeviceLock works on any computer using Windows NT 4.0 SP 6/2000/XP/Vista/7 and Windows Server 2003/2008. It supports 32-bit and 64-bit platforms. Windows Internet Explorer version 4.0 or later must be installed on computers running Windows NT 4.0 SP 6.

**Note:** NetworkLock, an extension to DeviceLock, does not work on computers running Windows NT 4.0 SP 6.

To install and use DeviceLock, you MUST have administrative privileges. If you are going to use DeviceLock only on a local computer, you must have local administrative privileges. If you are going to use DeviceLock throughout your network, you must have domain administrator privileges.

If you want to use DeviceLock on your network, you must have a functioning TCP/IP network protocol. However, DeviceLock can also work on stand-alone computers. A network is needed only if you want to control DeviceLock Service from a remote computer.

## **Deploying DeviceLock Service**

DeviceLock Service should be installed on the computer so you can control the access to devices on that computer. There are multiple ways to deploy DeviceLock Service to client systems.

### **Interactive Installation**

Run Setup (**setup.exe**) and follow the instructions that appear on the screen.



You should run **setup.exe** on each computer that is to be controlled with DeviceLock Service.

If you are upgrading a previous version, make sure that you have administrative access to DeviceLock Service, otherwise you will not be able to continue installation.

You must accept DeviceLock's End User License Agreement to continue the installation process.

On the **Customer Information** page, type your user name and organization. On this page, under **Install this application for**, you can specify for whom desktop shortcuts to DeviceLock management consoles (DeviceLock Management Console, DeviceLock Enterprise Manager and DeviceLock Service Settings Editor) will be created. You can select from the following options:

- Anyone who uses this computer (all users) Creates desktop shortcuts to DeviceLock management consoles for all users.
- **Only for me** Creates desktop shortcuts to DeviceLock management consoles only for the account that is installing DeviceLock.

	Devicel or
Please enter your information.	Proactive Endpoint Secu
User Name:	
Organization:	
Install this application for:	
and call on application from	
<ul> <li>Anyone who uses this computer (all users)</li> </ul>	
Anyone who uses this computer (all users)     Only for me ()	
Anyone who uses this computer (all users)     Only for me ()	

On the **Setup type** page, select the required setup type.

You have the following two choices: either install both DeviceLock Service and DeviceLock management consoles using the **Service + Consoles** option or install only DeviceLock Service using the **Custom** option and selecting the **DeviceLock Service** component.

🖁 DeviceLock Setup		
Setup Type Choose the setup type that	best suits your needs.	DeviceLock Proactive Endpoint Security
Please select a setup type.		
• Service + Consoles	DeviceLock Service, Devicel Group Policy Manager and D be installed.	Lock Enterprise Manager, DeviceLock DeviceLock Management Console will
O Server + Consoles	DeviceLock Enterprise Serve and DeviceLock Group Policy	er, DeviceLock Management Console y Manager will be installed.
Custom	Choose which program feat they will be installed. Record	ures you want installed and where mended for advanced users.
nstallShield	< Back	Next > Cancel

ustom Setup Select the program features you want installed.	DeviceLoc Proactive Endpoint Secu
lick on an icon in the list below to change how a f	eature is installed. Peature Description
This feature, and all subfeatures,  This feature will not be available.	will be installed on local hard drive. 008, n all like
	control to devices. This feature requires 10MB on your hard drive.
stall to: \Program Files\DeviceLock\	Change

**Note:** On the **Custom Setup** page, you can select the RSoP component to install. This component enables support for DeviceLock's Resultant Set of Policy planning mode on domain controllers. The RSoP component is required only when DeviceLock management consoles are installed, but DeviceLock Service is not installed on the computer. For more information on RSoP planning mode, refer to the <u>Microsoft documentation</u>.

On the **Custom Setup** page, you can change the default installation directory. By default, the DeviceLock installation directory is **%ProgramFiles%\DeviceLock**. To change the default installation directory, click **Change** to open the **Change Current Destination Folder** page.

🕲 DeviceLock Setup	X
Change Current Destination Folder Browse to the destination folder.	DeviceLock Proactive Endpoint Security
Look in:	
DeviceLock	E 2
DeviceLock Agent Plugins Projects	
Eolder name:	
InstalShield	
	OK Cancel

On the **Ready to Install the Program** page, click **Install** to begin the installation. Select the **Add DeviceLock shortcuts to the desktop** check box if you want to add DeviceLock Management Console (the MMC snap-in), DeviceLock Enterprise Manager and DeviceLock Service Settings Editor shortcuts to the desktop.

DeviceLock Setup Ready to Install the Program The wizard is ready to begin installation.	DeviceLoc Proactive Endpoint Secur
Click Install to begin the installation.	
If you want to review or change any of your installatio exit the wizard.	n settings, click Back. Click Cancel to
Add DeviceLock shortcuts to the desktop	
talShield	Install Cancel

If you choose to install DeviceLock management consoles as well, Setup may suggest that you generate a new DeviceLock Certificate.

DeviceL	ock Setup 🛛 🕅
2	Do you want to create the new DeviceLock Certificate (the private and public key pair)? Click "No" if you already have DeviceLock Certificate and you don't need to create the new key pair.
	<u>Yes</u> <u>N</u> o

You can always generate a new DeviceLock Certificate later, using the Certificate Generation Tool installed with DeviceLock management consoles. Hence, if at this step you are not sure whether you need the new certificate or not, just press the **No** button and continue the installation. For more information on DeviceLock Certificates, see "<u>DeviceLock Certificates</u>."

Also, if you select **Service + Consoles**, Setup may suggest that you load the DeviceLock license files. If you don't have the license files, click **Cancel** to install DeviceLock in a 30-day trial mode.

Select the DeviceLock license file(s)	? 🛛
Choose a directory with the license file(s) for DeviceLock. PRESS " INSTALL A 30-DAY TRIAL VERSION.	CANCEL" TO
C:\DOCUME~1\uaw\LOCALS~1\Temp\Temporary Directory 3 for devicelock-win32-7.0.0.28867-fre-enu-bin.zip\	
My Computer	
🖃 🎯 Desktop	^
My Documents	
July Computer     July Shoppy (A:)	
😑 🧼 Local Disk (C:)	
Cocuments and Settings	_
Program Files     Screenschatz	
WINDOWS	
a_0. CD Drive (Dr)	~
ок	Cancel

During the installation process, you can set special permissions for local devices.

Lock Devices	<b>X</b>
Lock automatically:     Ploppy Drives     Removable Devices     CD-ROMs, DVD-ROMs     Serial Ports     Parallel Ports     Windows Mobile Devices     Palm Devices     Phone     Claboard	Tape Devices USB Ports Infrared Ports FireWire Ports (IEEE 1394) Bluetooth Adapters WFF (802.11) Adapters Printers BlackBerry
Create local groups (Allow_Access_ Security Settings: Access control for USB HID (mou: Access control for USB printers Access control for USB sconners. Access control for USB storage d Access control for USB storage d Access control for USB and Firel/ Access control for Firel/Fire	to) if not existing se, keyboard, etc.) and still image devices adapters evices ine network cards ge devices (internal and external) ts (Windows 2000 and later) (Windows 2000 and later) in copy/paste clipboard operations is denied
0	QK Słap

Check devices you would like to set permissions to. Check the **Create local groups if not existing** flag to instruct Setup to create the special local user group Allow\_Access\_To\_ for each device type (e.g. Allow\_Access\_To\_Floppy for floppy drives), if these do not exist on the local computer.

Setup assigns **Read**, **Write**, **Format** and **Eject** generic rights to members of the Administrators group and the SYSTEM account. Members of the Allow\_Access\_To\_ group will have **Read**, **Write** and **Eject** generic rights.

Also, you can define <u>Security Settings</u> to exclude certain types of devices from the access check.

Check Access control for USB HID, Access control for USB printers, Access control for USB scanners and still image devices, Access control for USB Bluetooth adapters, Access control for USB storage devices or Access control for FireWire storage devices to allow DeviceLock Service to control security for Human Interface Devices (mouse, keyboard, etc.), printers, scanners and still image devices, Bluetooth adapters or storage devices (such as flash drives) plugged into the USB and FireWire port. To allow access control for USB and FireWire network cards, check Access control for USB and FireWire network cards. Otherwise, even if ports (USB and/or FireWire) are locked, these devices continue to function as usual. To allow access control for serial modems (internal and/or external), check Access control for serial modems. To disable locking of virtual (software emulated) CD-ROMs on Windows 2000 and later systems, uncheck Access control for virtual CD-ROMS. To disable control of virtual printers (those which print to files) on Windows 2000 and later systems, uncheck Access control for virtual printers. To allow access control for copy/paste clipboard operations between different applications, select the Access control for inter-application copy/paste clipboard operations check box. Otherwise, even if the clipboard is locked, access control for copy/paste operations between different applications is disabled. To disable FireWire controllers when the Everyone account has No Access permissions for the FireWire port device type, select the **Block FireWire controller if access is** denied check box.

Click **OK** to apply changes. Click **Skip** if you prefer to wait until after installation to set permissions to these devices using DeviceLock management consoles.

As soon as Setup has installed DeviceLock, it suggests that you point your default Internet browser to the DeviceLock Web site.



Clear the **Open DeviceLock home page** check box if you do not want to visit the DeviceLock Web site. Click **Finish** to finish the installation.

Note: To uninstall DeviceLock, do one of the following:

Use Add or Remove Programs in Control Panel to remove DeviceLock. - OR -Click Start, point to All Programs, point to DeviceLock, and then click Remove DeviceLock.

### **Unattended Installation**

DeviceLock also supports unattended (silent) setups. This provides an installation method that can be used from within a batch file. To install DeviceLock Service without user intervention, run Setup with the **/s** parameter (e.g. **c:\setup.exe /s**). There is a special configuration file for silent setups named **devicelock.ini**. The devicelock.ini file must be in the same directory as setup.exe. With this file, you can customize the installation parameters.

You can open and edit devicelock.ini in any text editor, for example in Notepad. Remove a semicolon (;) before the parameter to assign a new value or leave it to assign the default value.

There are two sections (**[Install]** and **[Misc]**) in this configuration file and each section has its own parameters:

### 1. [Install]

To install DeviceLock Service, specify the **Service** parameter:

### Service = 1

You can also install DeviceLock management consoles and the documentation, using **Manager** and **Documents** parameters.

If you want to just upgrade DeviceLock Service and do not want to change existing settings, use the **OnlyUpgradeService** parameter:

#### **OnlyUpgradeService = 1**

In this case Setup ignores all specified settings and only upgrades DeviceLock Service to the new version.

You can also define a destination directory for DeviceLock:

InstallDir = C:\Program Files\DeviceLock

Setup uses this directory if it can't find the previous installation of DeviceLock.

If you have purchased licenses for DeviceLock, you can also specify the location of the license files:

### **RegFileDir** = C:\Directory

where *C*:\*Directory* is where your license files are located.

You do not need to load the licenses, if you are installing only DeviceLock Service. They are required for DeviceLock management consoles and separately licensed components: ContentLock and NetworkLock.

To instruct DeviceLock Service to use a fixed port, specify the **FixedPort** parameter:

### **FixedPort** = [port number]

where *port number* – the fixed TCP port number that you want to use for the communication between DeviceLock Service and management consoles. To use dynamic ports for the RPC communication, specify 0 as a port number. By default, DeviceLock Service uses port 9132.

If the **CreateGroups** parameter is set to "1", Setup creates the special local user group Allow\_Access\_To\_ for each device type (e.g. Allow\_Access\_To\_Floppy for floppy drives), if these do not exist on the local computer.

To apply settings, permissions, audit and shadowing rules to DeviceLock Service, specify the path to the previously saved XML file in the **SettingsFile** parameter:

### SettingsFile = C:\settings.dls

This settings file can be created using DeviceLock Management Console, DeviceLock Group Policy Manager and/or DeviceLock Service Settings Editor.

### 2. [Misc]

If you want to run a program (e.g. batch file) after a successful install, you can specify the **Run** parameter:

#### **Run** = C:\mybatchfile.bat

To suppress an automatic restart even if Setup needs it, set the **DisableRestart** parameter to 1''.

### Installation via Microsoft Systems Management Server

The <u>unattended installation</u> allows you to deploy DeviceLock Service using Microsoft Systems Management Server (SMS). Use the package definition files (DevLock.pdf for SMS version 1.x and DevLock.sms for SMS version 2.0 and later) supplied with DeviceLock, located in the sms.zip file.

### Remote Installation via DeviceLock Management Console

DeviceLock Management Console (the MMC snap-in) supports remote installation to help system administrators set up a service on remote machines without ever having to physically go to them.

When you're trying to connect to a computer where DeviceLock Service is not installed or is outdated, the management console suggests that you install or update it.



Select the directory that contains all of the files needed for installation (such as DeviceLock Service.msi, DeviceLock Service x64.msi, DLRemoteInstaller.exe, and InstMsiW.exe).



These files are located in the DeviceLock installation directory. By default, the DeviceLock installation directory is **%ProgramFiles%\DeviceLock**.

By default, the DeviceLock Service installation files will be copied to the %ProgramFiles%\DeviceLock Agent folder if this service doesn't exist on this system. If the service exists on the system but its version is lower than 7.0, the management console will also copy the installation files to the default %ProgramFiles%\DeviceLock Agent folder. If the service exists on the system but its version is 7.0 or higher, the management console will copy the installation files to the directory of the old files and the old files will be replaced.

### Remote Installation via DeviceLock Enterprise Manager

DeviceLock Enterprise Manager contains the Install service plug-in that allows you to deploy DeviceLock Service automatically on all the selected computers in your network.

🛃 Scan Netwo	rk	? 2
	Select domain(s) and computer's type(s) Types TRAVEL_GROUP	Select Plug-in  Select Plug-in  Audit Log Viewer  Seport Permissions/Auditing  Report PnP Devices Set Service Settings Shadow Log Viewer Uninstall service  Settings
Show this dia	og at next startup	Scan Close

First, select computers where DeviceLock Service must be installed. DeviceLock Enterprise Manager allows you to select computers by their types and names. You can also load the computers list from an external file or select them from any LDAP tree (Active Directory, Novell eDirectory, OpenLDAP and so on).

Then, select the **Install service** plug-in and click the **Settings** button to specify the directory that contains all of the files needed for installation (such as DeviceLock Service.msi, DeviceLock Service x64.msi, DLRemoteInstaller.exe, and InstMsiW.exe). These files are located in the DeviceLock installation directory. By default, the DeviceLock installation directory is **%ProgramFiles%\DeviceLock**. You can also instruct DeviceLock Service to use the fixed TCP port for the communication with management consoles. To use dynamic ports for the RPC communication, select the **Dynamic ports** option. By default, DeviceLock Service uses port 9132.
Install options	? 🛛
Path to installation files	
C:\Program Files\DeviceLo	ocki
NOTE: The directory DLRemoteInstaller.e: Service.msi and Device	should contain ke, InstMsIW.exe, DeviceLock ceLock Service x64.msi files.
Oynamic ports	
O Specify port:	
	OK Cancel

By default, the DeviceLock Service installation files will be copied to the %ProgramFiles%\DeviceLock Agent folder if this service doesn't exist on this system. If the service exists on the system but its version is lower than 7.0, the Install service plug-in will also copy the installation files to the default %ProgramFiles%\DeviceLock Agent folder. If the service exists on the system but its version is 7.0 or higher, the Install service plug-in will copy the installation files to the directory of the old files and the old files will be replaced.

### **Installation via Group Policy**

This step-by-step instruction describes how to use Group Policy to automatically distribute DeviceLock Service to client computers. DeviceLock Service can be deployed in an Active Directory domain using the Microsoft Software Installer (MSI) package (DeviceLock Service.msi and DeviceLock Service x64.msi).

**Note:** Microsoft Windows Group Policy automated-program installation requires client computers that are running Windows 2000 or later.

If you use a custom MSI package with defined DeviceLock Service settings to deploy DeviceLock Service using Group Policy, these settings are not applied to client computers if any one of the following conditions is true:

- The default security is disabled on remotely running DeviceLock Services.

- The GPO applied to client computers has the **Override Local Policy** setting enabled.

For information about how to create a custom MSI package, see "Create MSI Package."

You can use Group Policy to distribute DeviceLock Service by using the following steps:

#### • Create a Distribution Point

To install DeviceLock Service, you must create a distribution point on the server. To create a distribution point, do the following:

- 1. Log on to the server computer as an administrator.
- 2. Create a shared network folder in which to place the MSI package.

- 3. Set permissions on the share to allow access to the distribution package.
- 4. Copy the MSI package (DeviceLock Service.msi and/or DeviceLock Service x64.msi) to the distribution point.

#### • Create a Group Policy Object

To create a Group Policy object (GPO) with which to distribute DeviceLock Service, do the following:

1. Start the Group Policy Management snap-in.

*If the Group Policy Management snap-in is not installed on your computer, you may use the Active Directory Users and Computers snap-in instead.* 

2. In the console tree, select your domain.

Group Policy Mana	igement				_ 🗆 ×
SE Elle Action View	v <u>W</u> indow <u>H</u> elp				_8×
⇔ → 🗈 🖬	1 🗗 🕑 😫				
Group Policy Manage	ment	vm2000ad.	com		
E B Domains	id.com	Linked Group	Policy Obje	ects Group Policy Inheritance	Delegation
E-00 vm2000	Create and Link a GPO He	re	<b>भ</b> ≜	GPO	Enfor
Def	Link an Existing GPO			🔊 Default Domain Policy	No
⊡∰ Des ⊛ @ Dor	Block Inheritance			S DeviceLock Group Policy C	bject No
⊕-@g Gro	New Organizational Unit				
Group Polic	Search				•
Create a GPO in this do	Change Domain Controller Remove	l			

3. Click **Create and Link a GPO Here** from the context menu of the domain item.

If you are using the Active Directory Users and Computers snap-in, right-click your domain, then click **Properties**, click the Group Policy tab, and then click **New**.

Active Directory Users a	and Computers	
∫ 🥥 Console Window <u>H</u> e	elp	_8×
Tree	sl2.com 5 objects	
Active Directory Users and (  Find  Acti	rom Here	Type builtinDomain Container Organizational Unit Container Container
Properties Help		

Active Directory Us	ers and Computers	
Gonsole Window	sl2.com Properties	? ×
Tree	General Managed By Group Policy	
	Current Group Policy Object Links for	sl2
	Group Policy Object Links	No Override Disabled
	DeviceLock Service distribution	
·	Group Policy Objects higher in the list have the hi	nhest priority.
	This list obtained from: sl_server2.sl2.com	groot priority.
	New Add Edit	Lip .
	Delete Properties	Do <u>m</u> n
	Block Policy inheritance	
	Close	Cancel Apply

- 4. Type the name that you want to call this policy, and then press ENTER.
- 5. In the console tree, select your group policy object, click the **Delegation** tab, and then click **Advanced**.



If you are using the Active Directory Users and Computers snap-in, click **Properties** on the **Group Policy** tab, and then click the **Security** tab.

DeviceLock Service distribution Properties		? ×
General Links Security		
News		1
	- 1-	Aga
P4HUSLAN-N14 (SL2\P4HUSLAN-N14\$)	- 16	Remove
P4RUSLAN-W2K (SL2\P4RUSLAN-W2K\$)		
P4SUPPORT (SL2\P4SUPPORT\$)		
P4SUPPORT_NT (SL2\P4SUPPORT_NT\$)		
P4SUPPORT_W2K (SL2\P4SUPPORT_W2K)	<sup>3]</sup> 🚽 📃	
Parmierione	Allow	Denu
	- stort	
Full Control		
Read		
Write		
Create All Child Objects		
Delete All Child Objects		
Apply Group Policy		
1		
Advanced		
OK	ncel	Apply
		LPPU

6. Click on the **Deny** check box next to **Apply Group Policy** for the security groups that you want to prevent from having this policy applied.

Click on the **Allow** check box for the groups to which you want to apply this policy. When you are finished, click **OK**.

#### • Assign a Package

To assign DeviceLock Service to computers that are running Windows 2000 or later:

- 1. Open the group policy object that you need in the Windows Group Policy Object editor (use either the Group Policy Management or Active Directory Users and Computers snap-in).
- 2. Under Computer Configuration, expand Software Settings.
- 3. Right-click **Software installation**, point to **New**, and then click **Package**.

sl2.com Properties			? ×	
Consultation and Sm	un Policu I			
gf Group Policy				
Action ⊻iew 🛛 🗢 ⇒ 🗈	• 6° 6 6			
Tree	Name	Version	Deployment state	Auto-install
DeviceLock Service distribution [s]     Computer Configuration     Software Settings     Software installation     Windows Settings     Software Template     Software Settings     Software Settings     Software Settings     Administrative Template     Administrative Template	Lew ▶ Package /iew ▶ Refresh Export List Properties Help			
Adds a package.				
Block Policy inheritance	Close Concel	A	aly	,

 In the **Open** dialog box, type the full Universal Naming Convention (UNC) path to the shared folder that contains the DeviceLock Service MSI package. For example: \\file server\share\DeviceLock Service.msi.

**Important:** Do not browse to the location. Ensure that you use the UNC path to the shared folder.

- 5. Click **Open**.
- 6. Click **Assigned**, and then click **OK**.

The package is listed in the right pane of the Group Policy window.

Deploy Software	? ×
Select deployment method:	
C Bublished	
<ul> <li>Assigned</li> </ul>	
C Advanced published <u>o</u> r a	ssigned
Select this option to Assign the a	application without modifications.
	OK Cancel

7. Close the Windows Group Policy Object editor. When the client computer starts, DeviceLock Service is automatically installed.



#### Upgrade a Package

If the previous version of DeviceLock Service was already deployed and you want to upgrade it to the new one:

- 1. Open the group policy object that contains the old DeviceLock Service package in the Windows Group Policy Object editor (use either the Group Policy Management or Active Directory Users and Computers snap-in).
- 2. Under Computer Configuration, expand Software Settings.
- 3. Right-click **Software installation**, point to **New**, and then click **Package**.



- In the **Open** dialog box, type the full Universal Naming Convention (UNC) path to the shared folder that contains the new DeviceLock Service MSI package. For example: \\file server\share\DeviceLock Service.msi.
- 5. Click **Open**.
- 6. Click **Assigned**, and then click **OK**.

The new package is listed in the right pane of the Group Policy window.

of Group Policy			
Action ⊻iew 🛛 🗢 → 🗈 💽	I 🗗 🖸 🕱		
Tree	Name 🛆	Version	Deployment state
New Group Policy Object [s] ser	🚰 DeviceLock Service	5.7	Assigned
Computer Configuration  Software Settings  Windows Settings  Mindows Settings  Mindows Settings  Software Installation  Software Settings  Mindows  Mindows Settings  Mindows Settings  Mindows  Mindows	DeviceLock Service (old)	5.62	Assigned
	•		Þ

7. Right-click the new package, click **Properties**, and then click the **Upgrades** tab.

	DeviceLock Service Properties	
	General Deployment Upgrades Categories Modifications Security	
Group Poli <u>Action Vie</u> Tree      New Group      @ New Group      @ Compute      On Soft	Packages that this package will upgrade:	
	Add <u>R</u> emove       ■     Required upgrade for existing packages	F
	OK Cancel Apply	

8. Click **Add**, select the old DeviceLock Service package you want to upgrade, click **Uninstall the existing package, then install the upgrade package**, and then click **OK**.

ld Upgrade Package	? >
Choose a package from	
Current Group Policy Object (GPO)	
C A specific GPO:	
	Browse
	<u></u>
Package to upgrade	
DeviceLock Service (old)	
1	
<ul> <li>Uninstall the existing package, then install</li> </ul>	the upgrade package
C Package can upgrade over the existing pa	sckage
Enclose carrapgings over the choosing pe	sonago
	EK Cancel

 Click **OK** to close the **Properties** window, close the Windows Group Policy Object editor. When the client computer starts, DeviceLock Service is automatically upgraded.

of Group Policy				_ 🗆 🗵
Action ⊻iew 🛛 🗢 ⇒ 🗈	📧 🖆 🗗 🛱			
Tree	Name 🛆	Version	Deployment state	Upgrading
New Group Policy Object [s] s	BeviceLock Service	5.7	Assigned	DeviceLock Service (old)
E . Computer Configuration	😤 DeviceLock Service (old)	5.62	Assigned	None
- Software Settings				
Software installatic				
Image: The setting the setting the setting the setting the setting the setting the set of the se				
- SmartLine DeviceLock				
Administrative Templa				
E 🛃 User Configuration				
Windows Settings				
	•			Þ

**Note:** Usually when you upgrade, the new DeviceLock Service MSI package detects its previously assigned package in GPO and automatically performs steps 7and 8 described above.

#### • Redeploy a Package

In some cases you may want to redeploy DeviceLock Service.

To redeploy a package:

- 1. Open the group policy object which contains the deployed package in the Windows Group Policy Object editor (use either the Group Policy Management or Active Directory Users and Computers snap-in).
- 2. Expand the **Software Settings** container that contains the **Software installation** item with which you deployed the package.

- 3. Click the **Software installation** container that contains the package.
- 4. In the right pane of the **Group Policy** window, right-click the program, point to **All Tasks**, and then click **Redeploy application**. *The following message is displayed: "Redeploying this application will reinstall the application everywhere it is already installed. Do you want to continue?"*
- 5. Click Yes.
- 6. Close the Windows Group Policy Object editor.

#### • Remove a Package

To remove DeviceLock Service:

- 1. Open the group policy object which contains the deployed package in the Windows Group Policy Object editor (use either the Group Policy Management or Active Directory Users and Computers snap-in).
- 2. Expand the **Software Settings** container that contains the **Software installation** item with which you deployed the package.
- 3. Click the **Software installation** container that contains the package.
- 4. In the right pane of the **Group Policy** window, right-click the program, point to **All Tasks**, and then click **Remove**.
- 5. Click **Immediately uninstall the software from users and computers**, and then click **OK**.
- 6. Close the Windows Group Policy Object editor.

Please keep in mind:

- Deployment occurs only when the computer starts up, not on a periodic basis. This prevents undesirable results, such as uninstalling or upgrading an application that is in use.
- DeviceLock Service will be copied to the %ProgramFiles%\DeviceLock Agent folder if this service doesn't exist on the system. If the service exists on the system but its version is lower than 7.0, DeviceLock Service will also be copied to the default %ProgramFiles%\DeviceLock Agent folder. If the service exists on the system but its version is 7.0 or higher, DeviceLock Service will be copied to the directory of the old version and the old version will be replaced.

# **Installing Management Consoles**

DeviceLock management consoles are the control interfaces that systems administrators use to remotely manage DeviceLock Service, DeviceLock Enterprise Server and DeviceLock Content Security Server.

The DeviceLock management consoles should be installed on the computer from which the administrator is going to manage DeviceLock's settings and run reports. It is not necessary to install management consoles on the server (domain controller or others), even if you are going to use DeviceLock Group Policy Manager to manage

settings via Active Directory Group Policy – you can do it from your local workstation (proper privileges required).

**Note:** In order to use DeviceLock Management Console (the MMC snap-in) and DeviceLock Service Settings Editor on computers with Windows NT 4.0, you should install the Microsoft Management Console update. You can download this update for free from the Microsoft's Web site: <u>http://www.microsoft.com/downloads/details.aspx?familyid=3F620A07-C996-4A81-</u> <u>AAD8-30134A43EC46&displaylang=en</u>.

Run Setup (setup.exe) and follow the instructions that appear on the screen.



You must accept the DeviceLock's End User License Agreement before continuing the installation process.

On the **Customer Information** page, type your user name and organization. On this page, under **Install this application for**, you can specify for whom desktop shortcuts to DeviceLock management consoles (DeviceLock Management Console, DeviceLock Enterprise Manager and DeviceLock Service Settings Editor) will be created. You can select from the following options:

- Anyone who uses this computer (all users) Creates desktop shortcuts to DeviceLock management consoles for all users.
- **Only for me** Creates desktop shortcuts to DeviceLock management consoles only for the account that is installing DeviceLock.

Customer Information	DeviceLoc
Please enter your information.	Proactive Endpoint Secur
User Name:	
Organization:	_
Install this application for:	
Install this application for: Anyone who uses this computer (all users)	
Install this application for:	

On the **Setup type** page, select the required setup type.

You have the following three choices: install both DeviceLock Service and DeviceLock management consoles using the **Service + Consoles** option, install both DeviceLock Enterprise Server and DeviceLock management consoles using the **Server + Consoles** option or install only DeviceLock management consoles using the **Custom** option and selecting the **DeviceLock Consoles** component.

Setup Type		Device lead
Choose the setup type that	best suits your needs.	Proactive Endpoint Security
Please select a setup type.		
• Service + Consoles	DeviceLock Service, Devic Group Policy Manager and be installed.	eLock Enterprise Manager, DeviceLock DeviceLock Management Console will
⊖Server + Consoles	DeviceLock Enterprise Serv and DeviceLock Group Poli	ver, DeviceLock Management Console cy Manager will be installed.
Custom	Choose which program fea they will be installed. Reco	atures you want installed and where mmended for advanced users.
et all Chiadd		
Andrew monte	< Back	Next > Cancel

Select	t the program features you want installed.	Proactive Endpoint Secu
lick on	an icon in the list below to change how a feature is	Installed. Feature Description This package contains DeviceLock Enterprise Manager, DeviceLock Group Policy
	This feature will be installed on local hard dr	rive. ze ock
	This feature, and all subfeatures, will be instructed.	stalled on local hard drive.
	× This feature will not be available.	Bon
		your hard drive.
stall to :\Progr	o: ram Files\DeviceLock\	Change

**Note:** On the **Custom Setup** page, you can select the RSoP component to install. This component enables support for DeviceLock's Resultant Set of Policy planning mode on domain controllers. The RSoP component is required only when DeviceLock management consoles are installed, but DeviceLock Service is not installed on the computer. For more information on RSoP planning mode, refer to the <u>Microsoft documentation</u>.

On the **Custom Setup** page, you can change the default installation directory. By default, the DeviceLock installation directory is **%ProgramFiles%\DeviceLock**. To change the default installation directory, click **Change** to open the **Change Current Destination Folder** page.

🕲 DeviceLock Setup	
Change Current Destination Folder Browse to the destination folder.	DeviceLock Proactive Endpoint Security
Look in:	
DeviceLock	E
DeviceLock Agent Plugins Projects	
Eolder name:	
Tortal Shald	
at the area in the second s	OK Cancel

DeviceLock ships with three different management consoles: DeviceLock Management Console (the MMC snap-in), DeviceLock Enterprise Manager and DeviceLock Group Policy Manager (integrates into the Windows Group Policy Editor). Installed together with other management consoles is DeviceLock Service Settings Editor, a tool used for creating and modifying external XML files with settings, permissions, audit and shadowing rules for DeviceLock Service.

On the **Ready to Install the Program** page, click **Install** to begin the installation. Select the **Add DeviceLock shortcuts to the desktop** check box if you want to add DeviceLock Management Console (the MMC snap-in), DeviceLock Enterprise Manager and DeviceLock Service Settings Editor shortcuts to the desktop.

Ready to Install the Program	Deviced
The wizard is ready to begin installation.	Proactive Endpoint Secur
Click Install to begin the installation.	
If you want to review or change any of your installati exit the wizard.	ion settings, click Back. Click Cancel to
Add DeviceLock shortcuts to the desktop	
La Result	

Setup may suggest that you generate a new DeviceLock Certificate.



You can always generate the new DeviceLock Certificate later, using the Certificate Generation Tool installed with DeviceLock management consoles. Hence, if at this step you are not sure whether you need the new certificate or not, just press the **No** button and continue the installation. For more information on DeviceLock Certificates, see "DeviceLock Certificates."

Also, Setup may suggest that you load the license files for DeviceLock. If you don't have the license files, click **Cancel** to install DeviceLock in a 30-day trial mode.

Select the DeviceLock license file(s)	? 🛛
Choose a directory with the license file(s) for DeviceLock. PRESS "CAN INSTALL A 30-DAY TRIAL VERSION. C:\DOCLIME~1\uaw\LOCALS~1\Temp\Temporary Directory 3 for devicelock-win32-7.0.0.28867-fre-enu-bin.zip\	ICEL" TO
ок	Cancel

If you opted to install DeviceLock Service as well, Setup suggests that you set special permissions for local devices.

	E	ices	Lock Devi
Cipboard  Create local groups (Allow_Access_to) if not existing  Security Settings:  Access control for USB HED (mouse, keyboard, etc.)  Access control for USB printers  Access control for USB scamers and still image devices  Access control for USB bluetooth adapters  Access control for USB storage devices  Access control for USB and FireWire network cards  Access control for FireWire storage devices  Access control for FireWire storage devices  Access control for Serial modems (internal) and external)	(394) rs	watically:       vy Drives       Tape Devices       USB Ports       OMs, DVD-ROMS       Infrared Ports       IPorts       FireWire Ports (IEEI       Iel Ports       Bluetooth Adapters       ows Mobile Devices       WFI (802: 11) Adap       Devices       Printers       BlackBerry	Lock autor Ploppy Remov CD-RC Serial Paralle Windo Palm C Phone
Access control for BireWire storage devices     Access control for BireWire storage devices     Access control for serial moderns (internal and external)		local groups (Allow_Access_to) if not existing Settings: ss control for USB HID (mouse, keyboard, etc.) ss control for USB printers ss control for USB scanners and still image devices ss control for USB storage devices ss control for USB storage devices	Create k Security S Access Access Access Access Access
Access control for virtual co-kolms (Windows 2000 and later)     Access control for virtual printers (Windows 2000 and later)     Access control for inter-application copy/paste clipboard operat     Block FireWire controller if access is denied	tions	s control for Drawin returns (cates) ss control for serial modens (internal and external) ss control for virtual CD-ROMs (Windows 2000 and later) ss control for virtual printers (Windows 2000 and later) ss control for inter-application copy/paste clipboard ope FireWire controller if access is denied	Access     Access     Access     Access     Access     Access     Access     Block f

Click **Skip** if you prefer to wait until after installation to set permissions for devices using DeviceLock management consoles. For more information regarding these settings, please read the <u>Deploying DeviceLock Service</u> section of this manual.

If you opted to install DeviceLock Enterprise Server as well, Setup suggests that you define its settings using the configuration wizard.

	and the second	
Cocal System acc	Journ	
This account:	VM2000AD \Administrator	Browse
Password:	•••••	
Confirm password:	•••••	
Connection settings		
Dumamia nasta		
O Dynamic ports		

For more information regarding these settings, please read the <u>Installing DeviceLock</u> <u>Enterprise Server</u> section of this manual.

As soon as Setup has installed DeviceLock, it suggests that you point your default Internet browser to the DeviceLock Web site.



Clear the **Open DeviceLock home page** check box if you do not want to visit the DeviceLock Web site. Click **Finish** to finish the installation.

You can locate and run DeviceLock management consoles from the **Programs** menu available by clicking the Windows **Start** button.



**Note:** DeviceLock Group Policy Manager integrates into Windows Group Policy Editor and is not available as a stand-alone application. In order to use DeviceLock Group Policy Manager, you must run the standard Windows Group Policy Editor.

To uninstall DeviceLock, do one of the following:

Use Add or Remove Programs in Control Panel to remove DeviceLock.

- OR -

Click **Start**, point to **All Programs**, point to **DeviceLock**, and then click **Remove DeviceLock**.

# Installing DeviceLock Enterprise Server

DeviceLock Enterprise Server is the optional component for centralized collection and storage of shadow data and audit logs. Also, DeviceLock Enterprise Server can monitor remote computers in real-time, checking DeviceLock Service status (running or not), policy consistency and integrity.

In order to use DeviceLock Enterprise Server on Windows NT 4.0 SP6 and Windows 2000 computers, you should install Microsoft Data Access Components (MDAC) version 2.8 or later. MDAC is available for free download at the Microsoft Web site: <a href="http://www.microsoft.com/downloads/details.aspx?familyid=78cac895-efc2-4f8e-a9e0-3a1afbd5922e&displaylang=en">http://www.microsoft.com/downloads/details.aspx?familyid=78cac895-efc2-4f8e-a9e0-3a1afbd5922e&displaylang=en</a>.

## **Planning Infrastructure**

You can install several DeviceLock Enterprise Servers on different computers across your network to uniformly spread the network load.

DeviceLock Enterprise Server uses MS SQL Server to store its data. Hence, it is necessary to have MS SQL Server installed and started in your network before installing DeviceLock Enterprise Server. If you don't have MS SQL Server, you can install the free edition called SQL Server Express Edition available for free download at the Microsoft Web site:

http://www.microsoft.com/sqlserver/2005/en/us/express.aspx.

It is not necessary to run MS SQL Server and DeviceLock Enterprise Server on the same machine. Moreover, for performance and reliability reasons, it is better to install DeviceLock Enterprise Server on a separate computer.

There are three scenarios for connecting DeviceLock Enterprise Server and MS SQL Server. You should decide which scenario best fits your needs before installing DeviceLock Enterprise Server:

- 1. ONE-TO-ONE: you install one DeviceLock Enterprise Server and connect it to one Microsoft SQL Server. This scenario is most appropriate for small networks (up to several hundreds of computers).
- MANY-TO-MANY: you install several DeviceLock Enterprise Servers and connect each of them to its own Microsoft SQL Server. This scenario is typical for medium and large networks geographically distributed across a variety of segments.
- 3. MANY-TO-ONE: you install several DeviceLock Enterprise Servers and connect all of them to the one Microsoft SQL Server. This scenario could be used for medium and large networks with a powerful (large amount of memory and free storage space) dedicated machine for Microsoft SQL Server.

## **Interactive Installation**

Run Setup (**setup.exe**) and follow the instructions that appear on the screen. You must run **setup.exe** on each computer targeted for DeviceLock Enterprise Server installation.



You must accept the DeviceLock End User License Agreement before continuing the installation process.

On the **Customer Information** page, type your user name and organization. On this page, under **Install this application for**, you can specify for whom desktop shortcuts to DeviceLock management consoles (DeviceLock Management Console, DeviceLock Enterprise Manager and DeviceLock Service Settings Editor) will be created. You can select from the following options:

- Anyone who uses this computer (all users) Creates desktop shortcuts to DeviceLock management consoles for all users.
- **Only for me** Creates desktop shortcuts to DeviceLock management consoles only for the account that is installing DeviceLock.

ustomer Information	DeviceLoc
Please enter your information.	Proactive Endpoint Secu
User Name:	
[	
Organization:	_
Install this application for:	
<ul> <li>Anyone who uses this computer (all users)</li> </ul>	
Only for me ()	

On the **Setup type** page, select the required setup type.

You have the following two choices: either install both DeviceLock Enterprise Server and DeviceLock management consoles using the **Server + Consoles** option or install only DeviceLock Enterprise Server using the **Custom** option and selecting the **DeviceLock Enterprise Server** component.



🔀 DeviceLock Setup	X
Custom Setup Select the program features you want installed.	DeviceLock Proactive Endpoint Security
Click on an icon in the list below to change how a feature	is installed. Feature Description This package contains
This feature will be installed on local hard	drive. 008, installed on local hard drive.
X This feature will not be available.	
	This feature requires 5037KB on your hard drive.
Install to: C:\Program Files\DeviceLock\	Change
InstallShield Help Space < Back	Next > Cancel

**Note:** On the **Custom Setup** page, you can select the RSoP component to install. This component enables support for DeviceLock's Resultant Set of Policy planning mode on domain controllers. The RSoP component is required only when DeviceLock management consoles are installed, but DeviceLock Service is not installed on the computer. For more information on RSoP planning mode, refer to the <u>Microsoft documentation</u>.

On the **Custom Setup** page, you can change the default installation directory. By default, the DeviceLock installation directory is **%ProgramFiles%\DeviceLock**. To change the default installation directory, click **Change** to open the **Change Current Destination Folder** page.

DeviceLock Setup	X
Change Current Destination Folder Browse to the destination folder.	DeviceLock Proactive Endpoint Security
Look in:	
DeviceLock	👱 🗈 💌
Plugins Projects	
C:\Program Files\DeviceLock\	
stallShield	
	OK Cancel

On the **Ready to Install the Program** page, click **Install** to begin the installation. Select the **Add DeviceLock shortcuts to the desktop** check box if you want to add DeviceLock Management Console (the MMC snap-in), DeviceLock Enterprise Manager and DeviceLock Service Settings Editor shortcuts to the desktop.

🔀 DeviceLock Setup	
Ready to Install the Program The wizard is ready to begin installation.	DeviceLock Proactive Endpoint Security
Click Install to begin the installation.	
If you want to review or change any of your installati exit the wizard.	on settings, click Back. Click Cancel to
Add DeviceLock shortcuts to the desktop	
InstallShield	Install Cancel

If you selected to install DeviceLock management consoles as well, Setup may suggest that you generate a new DeviceLock Certificate.

DeviceL	ock Setup
?	Do you want to create the new DeviceLock Certificate (the private and public key pair)? Click "No" if you already have DeviceLock Certificate and you don't need to create the new key pair.

You can always generate the new DeviceLock Certificate later, using the Certificate Generation Tool installed with DeviceLock management consoles. Hence, if at this step you are not sure whether you need the new certificate or not, just press the **No** button and continue the installation. For more information on DeviceLock Certificates, see "DeviceLock Certificates."

If Setup detects that MS SQL Server is not running on the local computer but its installation package is available, Setup suggests that you run the MS SQL Server installation.

DeviceL	ock Setup 🛛 🕅
2	SQL Server is not running on the local computer. Do you want to install it?
	Yes No

If you don't want to install MS SQL Server on the local computer or it is already installed but just not started, press the **No** button.

During the installation process, you must configure DeviceLock Enterprise Server and define its main settings using the special wizard.

If you are installing an upgrade or just reinstalling DeviceLock Enterprise Server and want to keep its current configuration, you don't need to go through this wizard again – just press the **Cancel** button to close the wizard and keep all existing settings unchanged.

In case you need to change some parameters but keep others – edit only needed parameters and go through all the wizard's pages up to the **Finish** button on the very last page.

**Note:** If you are installing DeviceLock Enterprise Server for the first time (there are no existing settings on this computer yet) and you cancel the configuration wizard upon opening, Setup will not be able to install DeviceLock Enterprise Server's service, so you'll need to run the configuration wizard again.



If you press the **No** button to continue without installing the DeviceLock Enterprise Server's service, you will need to run Setup later and install the service anyway.

On the first page of the wizard you can opt to install DeviceLock Enterprise Server's service and define its startup parameters.

DeviceLock Enterp	rise Server	×
Log on as O Local System ac	count	
<ul> <li>This account:</li> </ul>	VM2000AD \Administrator Browse	וכ
Password:	•••••	
Confirm password:	•••••	
an account in th have administra	e Domain Admins group. DeviceLock Enterprise Server must tive access to every computer that is trying to connect to it.	
<ul> <li>Dynamic ports</li> </ul>		
O Fixed TCP port		
	< Back Next > Cancel	

#### Log on as

First of all, you should choose an account under which the DeviceLock Enterprise Server's service will start. As many other Windows services, the DeviceLock Enterprise Server's service can start under the special local system account (the SYSTEM user) and on behalf of any user.

To start the service under the SYSTEM user, select the **Local System account** option. Keep in mind that the process working under the SYSTEM user can't access shared network resources and authenticates on remote computers as an anonymous user. Therefore, DeviceLock Enterprise Server configured to run under the SYSTEM user is not able to store shadow files on the remote computer (e.g. on the file

server) and it must use DeviceLock Certificate for authentication on DeviceLock Services running on remote computers.

For more information about authentication methods, please read the description of the <u>Certificate Name</u> parameter.

To start the service on behalf of the user, select the **This account** option, enter the user's account name and the password. It is recommended to use a user account that has administrative privileges on all the computers where DeviceLock Service is running. Otherwise, you will need to use DeviceLock Certificate authentication.

If you're installing DeviceLock Enterprise Server in the domain environment, we recommend that you use a user account that is a member of the Domain Admins group. Since Domain Admins is a member of the local group Administrators on every computer in the domain, members of Domain Admins will have full access to DeviceLock Service on every computer.

Also, don't forget that if DeviceLock Security is enabled on remotely running DeviceLock Services to protect them against local users with administrative privileges, the user's account specified in the **This account** option must be also in the list of DeviceLock Administrators with **Full access** rights. Otherwise, you'll need to use DeviceLock Certificate authentication.

#### **Connection settings**

You can instruct DeviceLock Enterprise Server to use a fixed TCP port for communication with the management console, making it easier to configure a firewall. Type the port number in **Fixed TCP port**. To use dynamic ports for RPC communication, select the **Dynamic ports** option. By default, DeviceLock Enterprise Server is using the 9133 port.

Press the **Next** button to start the DeviceLock Enterprise Server's service and to proceed to the second page.

If the current user doesn't have full administrative access to DeviceLock Enterprise Server (in case it already exists and you're installing an upgrade), the configuration wizard will not be able to install the service and apply changes. Also, the similar error may occur when the current user doesn't have local administrative privileges on the computer where DeviceLock Enterprise Server is installing.



If you've specified an incorrect user name for the **This account** option or the wrong user password, DeviceLock Enterprise Server will not be able to start.



You will be notified if the user's account specified for the **This account** option is not a member of the Domain Admins group.



You may continue by pressing the **Yes** button. However keep in mind that in this case either the specified user must have full administrative access to all remotely running DeviceLock Services or DeviceLock Certificate (the public key) must be installed on every computer with DeviceLock Service.

If the user's account specified for the **This account** option doesn't have the Log On As A Service system privilege, the wizard automatically assigns it. This privilege is needed to start the service on behalf of the user.



If all of the service's startup parameters were specified correctly, the wizard starts DeviceLock Enterprise Server.

Starting service	
Please wait while the program is interacting with a s	ervice.
Starting service DLServer on Local Computer	
	Cancel

It takes some time (up to a minute) before the DeviceLock Enterprise Server's service is started and the wizard's second page is displayed.

On the second page, you can define the list of users that have administrative access to DeviceLock Enterprise Server and install DeviceLock Certificate (the private key).

DeviceLock Enterprise Server	
F Enable Default Security	
Users	
VM2000AD \D omain Admins	Full access
VM2000AD\Test	Read-only
Add Delete Full access  Add Delete Full access Add October Stranger Strange	have local
DeviceLock Certificate [05/11/2006 01:28:52 PM]	Remove
< Back Next	> Cancel

#### **Enable Default Security**

In the default security configuration all users with local administrator privileges (i.e. members of the local Administrators group) can connect to DeviceLock Enterprise Server using a management console and change its setting and run reports.

To turn on the default security, check the **Enable Default Security** flag.

If you need to define more granular access to DeviceLock Enterprise Server, turn off the default security by unchecking the **Enable Default Security** flag.

Then you need to specify authorized accounts (users and/or groups) that can connect to DeviceLock Enterprise Server. To add a new user or user group to the list of accounts, click on the **Add** button. You can add several accounts simultaneously.

To delete a record from the list of accounts, use the **Delete** button. Using Ctrl and/or Shift you can highlight and remove several records simultaneously.

To define which actions are to be allowed for a user or user group, set the appropriate rights:

- **Full access** to enable full access to DeviceLock Enterprise Server. Users can change settings and run reports.
- **Change** to enable change access to DeviceLock Enterprise Server. Users can change settings, install/uninstall DeviceLock Enterprise Server and run reports, but they can't add new users to the list of authorized accounts that can connect to DeviceLock Enterprise Server or change access rights for existing users in this list.
- **Read-only** to enable only read access to DeviceLock Enterprise Server. Users can run reports and view settings, but can't modify anything.

**Note:** We strongly recommend that accounts included in this list have local administrator privileges because, in some instances, installing, updating and uninstalling DeviceLock Enterprise Server's service may require access rights to Windows Service Control Manager (SCM) and shared network resources.

#### **Certificate Name**

You may need to deploy the private key to DeviceLock Enterprise Server if you want to enable authentication based on DeviceLock Certificate.

There are two methods of DeviceLock Enterprise Server authentication on remotely running DeviceLock Services:

- User authentication the DeviceLock Enterprise Server's service is running under the user's account that has full administrative access to DeviceLock Service on the remote computer. For more information on how to run DeviceLock Enterprise Server on behalf of the user, please read the description of the Log on as parameter.
- DeviceLock Certificate authentication in situations when the user under which DeviceLock Enterprise Server is running can't access DeviceLock Service on the remote computer, you must authenticate based on a DeviceLock Certificate.

The public key should be installed on DeviceLock Service and the corresponding private key on DeviceLock Enterprise Server.

To install DeviceLock Certificate, press the ... button, and select the file with a private key. To remove DeviceLock Certificate, press the **Remove** button.

For more information regarding DeviceLock Certificate, please read the <u>DeviceLock</u> <u>Certificates</u> section of this manual.

Press the **Next** button to apply changes and proceed to the third page of the configuration wizard.

From this page, you can load your DeviceLock licenses.

DeviceLock Enterprise Server	×
License information:	
You have 0 valid license(s) installed:	J
PLEASE REMEMBER THAT THIS IS A 30-DAY TRIAL VERSION!	
I	1
Reset Load License(s)	1
< Back Next > Cancel	1
	-

#### License information

If you've purchased a license for DeviceLock, you should load this license into DeviceLock Enterprise Server.

DeviceLock Enterprise Server handles only the licensed number of DeviceLock Services. For example, if you have a license for 100 computers but there are 101 DeviceLock Services working in your network, DeviceLock Enterprise Server will work with only first 100 DeviceLock Services and ignore the remaining one.

To load the license, press the **Load License(s)** button and select the license file.

You can load several license files in series – one by one.

If there are no valid licenses loaded, DeviceLock Enterprise Server works in the trial mode and can handle only two DeviceLock Services.

**Note:** If a computer with DeviceLock Service leaves the network, DeviceLock Enterprise Server will handle its replacement only after a restart or after 6 hours.

Press the **Next** button to install licenses and proceed to the fourth page.

On the fourth page, you can configure database parameters.

Database name:	DevicelockDB	
Connection type:	ODBC Driver	]
<u>S</u> QL Server name:	VM2000SERVER\VMINSTANCE	Browse
Login name: Password:	\$8 xxxxxxx	-
Login name:	sa	_
	Test Connection	
Store shadow file	is in SQL Server	
Store path:	%SystemRoot%\DLSTORE	Browse

#### Database name

You must specify the name of the database in SQL Server that will be used to store the DeviceLock Enterprise Server data. The default name suggested by the wizard is **DeviceLockDB**.

**Note:** You should not create a database with the specified name manually because the configuration wizard creates the database automatically or uses the existing one.

#### **Connection type**

There are two ways to define a connection to SQL Server:

1. **ODBC Driver** – you enter the name of SQL Server in **SQL Server name** and select the authentication mode (Windows or SQL Server).

The **SQL Server name** parameter must contain not just the name of the computer where SQL Server is running but the name of SQL Server itself. Usually the SQL Server name consists of two parts: the computer name and the instance name divided by a backslash (e.g. computer\instance). Sometimes the instance name is empty (default) and you can use the computer name as an SQL Server name. To retrieve SQL Server names available in your local network, press the **Browse** button. (You should have access to the remote registry of the SQL Server machine to retrieve the instance name.)

If the **SQL Server name** parameter is empty, it means that SQL Server is running on the same computer as DeviceLock Enterprise Server and has an empty (default) instance name.

To establish a connection to SQL Server, you must also configure authentication parameters.

Select the **Windows authentication** option to authenticate on SQL Server under the account used to run DeviceLock Enterprise Server's service.

If the service is running under the SYSTEM user and SQL Server is located on the remote computer, service will not be able to connect to SQL Server since the SYSTEM user doesn't have a right to access the network. For more information on how to run DeviceLock Enterprise Server on behalf of the user, please read the description of the Log on as parameter.

Select the **SQL Server authentication** option to allow SQL Server to perform the authentication itself by checking the login and password previously defined. Before selecting the **SQL Server authentication** option, make sure that your SQL Server was configured to use mixed-mode authentication.

Enter the SQL user name (login) in **Login name** and its password in **Password**.

**Note:** Windows Authentication is much more secure than SQL Server Authentication. When possible, you should use Windows Authentication.

2. **System Data Source** – you select the predefined system data source from the **Data Source Name** list.

To define data sources, use the **Data Sources (ODBC**) applet from **Control Panel** -> **Administrative Tools**.

🐼 ODBC D	ata Source	Administra	ator				? 🗙
User DSN	System DSN	File DSN	Drivers	Tracing	Connectio	n Pooling Al	bout
System D	ata Sources:						
Name	Dr	ver				Add.	
VM2000	SERVER SG	L Server				Remo	ve
						Configu	re
An DDBC System data source stores information about how to connect to the indicated data provider. A System data source is visible to all users on this machine, including NT services.							
	[	OK		ancel	Apply	н	lelp

If, in the data source configuration, SQL Server Authentication was chosen, then you also need to specify the SQL user name (login) in **Login name** and its password in **Password**. If Windows Authentication was selected, then you should leave these fields blank.

To refresh the **Data Source Name** list, press the **Refresh** button.

When connection to SQL Server is defined you may want to test it. Press the **Test Connection** button to make sure that all the parameters were specified correctly.

Test Connection	
Testing the connection to SQL Server	<u>×</u>
The connection was successful.	
,	
	Close

Please note that it only checks connectivity and your access rights to SQL Server. If there are problems with the database or your access rights to this database, you don't see those problems in the **Test Connection** dialog box.

If some connection parameters were specified incorrectly, you may see one of these errors:

- SQL Server does not exist or access denied you've specified an incorrect name of SQL Server in the SQL Server name parameter or the remote SQL Server's computer is not accessible. It is possible that you've specified the name of the computer where SQL Server is running but this SQL Server also has an instance name which should be specified as well (e.g. computer\instance).
- Login failed for user 'COMPUTER\_NAME\$' you've selected Windows Authentication but the user account used to run the DeviceLock Enterprise Server service can't get access to the computer with SQL Server. It may happen when the service starts either under the SYSTEM user or on behalf of a user that doesn't have local administrative privileges on the remote SQL Server's computer.
- Login failed for user 'user\_name' you've selected SQL Server Authentication and either specified an incorrect SQL user name (login) or the wrong password for it. Please note that SQL users are different from Windows users and you can't use the regular Windows account in the Login name parameter. SQL users exist only in SQL Server and to manage them you

should use SQL Server management consoles (such as Microsoft SQL Server Management Studio).

- Login failed for user 'user\_name'. The user is not associated with a trusted SQL Server connection you've selected SQL Server Authentication but your SQL Server doesn't support this mode. You should either use Windows Authentication or allow your SQL Server to work in the mixed mode (SQL Server and Windows Authentication mode).
- Login failed for user ". The user is not associated with a trusted SQL Server connection – the data source you've specified in Data Source Name was configured to use the SQL Server Authentication mode but the Login name parameter is empty.
- Data source name not found and no default driver specified you've selected System Data Source from the Connection type list and specified either an empty or non-existent name in Data Source Name.

#### Store shadow files in SQL Server

There are two modes of storing binary data: data can be stored in SQL Server or it can be stored on the disk.

To store data in SQL Server, check the Store shadow files in SQL Server flag.

If you decided to store binary data in SQL Server, we recommend that you dramatically increase the maximum file size parameter for the transaction log of the database specified in **Database name**. Otherwise, SQL Server may fail to handle the large amount of data (hundreds of megabytes) in one transaction. Also, it is recommended that you increase the maximum amount of memory available for SQL Server and turn on the PAE (Physical Address Extension) feature.

For more information on how to tune up your SQL Server for storing large amounts of data, please read the article available at the Microsoft Web site: <a href="http://technet.microsoft.com/en-us/library/cc966420.aspx">http://technet.microsoft.com/en-us/library/cc966420.aspx</a>.

To store data on the disk, uncheck the **Store shadow files in SQL Server** flag. In this case only links to the binary data and some additional information are stored in SQL Server.

When stored on the disk, data files are located by the path specified in the **Store path** parameter. To choose the folder where files should be stored, you can use the **Browse** button.

You can also specify the network shared resource (e.g. \\server\dlstore) that will be used as storage. Make sure that the user account used to run the DeviceLock Enterprise Server service has full access to this network resource.

**Note:** It is recommended to store binary data on the disk.

Press the **Next** button to apply changes and proceed to the last page.

DeviceLock Enterprise Server		
Verifying store path ("%5ystemHod	ot%\DLSTORE"]	<u>^</u>
0K!		
Connecting to SQL Server		
Creating the database		
The database creation completed	successfully.	
		~
,		
	< Back Finish	Cancel

It takes some time to create the database specified in **Database name** if it does not exist on this SQL Server yet. If the database already exists and it has the proper format (i.e. was created by DeviceLock Enterprise Server) then DeviceLock Enterprise Server keeps all existing data and uses this database.

**Note:** If necessary, DeviceLock automatically updates the database to the latest version.

If some parameters on the previous wizard's page were specified incorrectly, you may see one of these errors:

- [2] The system cannot find the file specified you've configured DeviceLock Enterprise Server to store binary data on the disk but the path specified in **Store path** is incorrect. If you've specified the shared network resource then it is possible that this network resource is not accessible.
- Failed to verify store path. [5] Access is denied the path specified in the Store path parameter is correct, but the user account used to run the DeviceLock Enterprise Server service doesn't have full access to files by this path.
- **CREATE DATABASE permission denied in database 'name'** the user's account (login) used to connect to SQL Server doesn't have enough privileges to create the database. The login should have at least the dbcreator Server

role (see **Server Roles** in **Login Properties** of Microsoft SQL Server Management Studio).

- The server principal "user\_name" is not able to access the database "name" under the current security context – the user's account (login) used to connect to SQL Server doesn't have access to the existing database. The login should be mapped to this database (see User Mapping in Login Properties of Microsoft SQL Server Management Studio).
- SELECT permission denied on object 'name', database 'name', schema 'name' – the user's account (login) used to connect to SQL Server doesn't have read/write access to the existing database. The login should have at least db\_datareader and db\_datawriter Database roles (see User Mapping in Login Properties of Microsoft SQL Server Management Studio).
- **Invalid object name 'name'** the database specified in the **Database name** parameter already exists in this SQL Server but has an incorrect format. It happens when you are trying to use the database that was not created by DeviceLock Enterprise Server or if the database was corrupted.
- **DeviceLock Database has an unsupported format** the database specified in the **Database name** parameter already exists but is outdated. This existing database has an unsupported format so it can't be automatically upgraded to the new format. You should either use another database or create a new one.
- DeviceLock Database has a format that is not supported by the current server version the database specified in the Database name parameter already exists but it was created by the more recent version of DeviceLock Enterprise Server. You should either use the latest version of DeviceLock Enterprise Server or use another database (or create a new one).

Also, some of the SQL Server connection errors <u>described above</u> may be displayed here as well.

Use the **Back** button to return to the previous page of the wizard and make necessary changes.

If there are no errors, press the **Finish** button to close the wizard and continue the installation process.

As soon as Setup has installed DeviceLock, it prompts you to point your default Internet browser to the DeviceLock Web site.



Clear the **Open DeviceLock home page** check box if you do not want to visit the DeviceLock Web site. Click **Finish** to finish the installation.

**Note:** To uninstall DeviceLock, do one of the following:

```
Use Add or Remove Programs in Control Panel to remove DeviceLock.
- OR -
Click Start, point to All Programs, point to DeviceLock, and then click Remove
DeviceLock.
```

# Installing DeviceLock Content Security Server

Follow these steps to install DeviceLock Content Security Server:

- Step 1. Prepare for the installation
- Step 2. Start the installation
- Step 3. Configure DeviceLock Content Security Server and complete the installation.

#### Step 1. Prepare for the installation

Before you install DeviceLock Content Security Server, consider the following important notes:

• The computer on which you install DeviceLock Content Security Server must meet the following system requirements:

Operating System	Microsoft Windows NT 4.0 Service Pack (SP) 6, Windows 2000, Windows XP, Windows Server 2003, Windows Server 2008, Windows Vista, or Windows 7. Installation is supported on both the 32-bit and the 64-bit editions of the operating system.
Web Browser	Microsoft Internet Explorer version 4.0 or later must be installed on computers running Windows NT 4.0 SP 6.
Hard Disk Space	19 MB

- You must have administrator permissions to install DeviceLock Content Security Server.
- For optimal performance and reliability, we recommend that you install DeviceLock Enterprise Server and DeviceLock Content Security Server on different computers.
- There is a special Search Server license which you must purchase for DeviceLock Content Security Server. You can use the same license on an unlimited number of computers running DeviceLock Content Security Server. The Search Server licensing model is based on the number of log entries to be indexed for full-text search. Each license allows Search Server to index 1,000 entries from the shadow logs (Shadow Log and Deleted Shadow Log), and 5,000 entries from every other log (Audit Log, Server Log, and Monitoring Log). Depending on the actual number of log entries on your DeviceLock Enterprise Servers, you can purchase as many licenses as required. If you use several licenses for Search Server, it can index as many log entries as the combined licenses allow. The trial period for DeviceLock Content Security Server is 30 days. During the trial period, Search Server can index 2,000 entries from the shadow logs and 10,000 entries from every other log.
- In case you have several DeviceLock Enterprise Servers on your network, you
  can also install several DeviceLock Content Security Servers to spread the
  load. However, this approach only makes sense if all these DeviceLock
  Enterprise Servers are not connected to the same Microsoft SQL Server (i.e.
  not in the "MANY-TO-ONE" mode).
- When you have several DeviceLock Content Security Servers installed each Search Server will have its own search index. Hence, you have to connect to every DeviceLock Content Security Server and run the same search queries on every Search Server in order to get the complete result set from all the data stored on all DeviceLock Enterprise Servers.
- We strongly recommend that you exit all Windows programs before you start Setup.

#### Step 2. Start the installation

Use this procedure to begin the installation process.

#### To start the installation

1. Open the **DeviceLock.zip** file, and then double-click the **setup\_dlcss.exe** file to start the Setup program.

You must run the Setup program on each computer on which you want to install DeviceLock Content Security Server.

- 2. Follow the instructions in the Setup program.
- On the License Agreement page, read the License Agreement and then click I accept the terms in the license agreement to accept the licensing terms and conditions and proceed with the installation.
- 4. On the **Customer Information** page, type your user name and organization, and then click **Next**.
- 5. On the **Destination Folder** page, accept the default installation location or click **Change** to modify the path as needed. Click **Next**.

*The default installation directory is %ProgramFiles%\DeviceLock Content Security Server.* 

6. On the **Ready to Install the Program** page, click **Install** to begin the installation.

The DeviceLock Content Security Server wizard starts.

If you are installing an upgrade or just re-installing DeviceLock Content Security Server and want to keep its current configuration, you do not need to go through this wizard again – just click **Cancel** to close the wizard and keep all existing settings unchanged.

In case you need to change some parameters but keep others – edit only needed parameters and go through all the wizard's pages up to the **Finish** button on the final page.

**Note:** If you are installing DeviceLock Content Security Server for the first time (there are no existing settings on this computer yet) and you cancel the configuration wizard upon opening, Setup will not be able to install DeviceLock Content Security Server's service, so you will need to run the configuration wizard again.

# Step 3. Configure DeviceLock Content Security Server and complete the installation

The DeviceLock Content Security Server wizard opens automatically during the installation process. This wizard will guide you through the required settings you must configure to use DeviceLock Content Security Server.
The first page of the wizard looks like this:

DeviceLock Content Security	y Server	×
Log on as		
Local System account		
⊙ <u>This account</u>	Browse	)
Password:		
Confirm password:		
Server must have administra Server that it is trying to con	hard warms group. DeviceLock Content Security tive access to every DeviceLock Enterprise nect to.	
Connection settings		
<ul> <li>Dynamic ports</li> </ul>		
O Eixed TCP port:		
	KBack Next> Cancel	

On this page, you configure startup options for the DeviceLock Content Security Server service.

#### Log on as

First of all, you should choose an account under which the DeviceLock Content Security Server service will start. As with many other Windows services, the DeviceLock Content Security Server service can start under the special local system account (the SYSTEM user) and on behalf of any user.

To start the service under the SYSTEM user, select the **Local System account** option. Keep in mind that the process working under the SYSTEM user cannot access shared network resources and authenticates on remote computers as an anonymous user. Therefore, DeviceLock Content Security Server configured to run under the SYSTEM user is not able to access DeviceLock Enterprise Server running on the remote computer and it must use DeviceLock Certificate for authentication on it.

For more information about authentication methods, please read the description of the <u>Certificate Name</u> parameter.

To start the service on behalf of the user, select the **This account** option, enter the user's account name and the password. It is recommended to use a user account that has administrative privileges on all the computers where DeviceLock Enterprise Server is running. Otherwise, you will need to use DeviceLock Certificate authentication.

If you are installing DeviceLock Content Security Server in the domain environment, we recommend that you use a user account that is a member of the Domain Admins

group. Since Domain Admins is a member of the local group Administrators on every computer in the domain, members of Domain Admins will have full access to DeviceLock Enterprise Server on every computer.

Also, do not forget that if Default Security is disabled on remotely running DeviceLock Enterprise Server, the user's account specified in the **This account** option must be also in the list of Server Administrators with at least **Read-only** access rights on that DeviceLock Enterprise Server. Otherwise, you will need to use DeviceLock Certificate authentication.

### **Connection settings**

You can instruct DeviceLock Content Security Server to use a fixed TCP port for communication with the management console, making it easier to configure a firewall. Type the port number in **Fixed TCP port**. To use dynamic ports for RPC communication, select the **Dynamic ports** option. By default, DeviceLock Content Security Server uses port 9134.

Click **Next** to start the DeviceLock Content Security Server service and to proceed to the second page.

If the current user does not have full administrative access to DeviceLock Content Security Server (in case it already exists and you're installing an upgrade), the configuration wizard will not be able to install the service and apply changes. Also, a similar error may occur when the current user does not have local administrative privileges on the computer where DeviceLock Content Security Server is installing.



If you have specified an incorrect user name for the **This account** option or the wrong user password, DeviceLock Content Security Server will not be able to start.



You will be notified if the user's account specified for the **This account** option is not a member of the Domain Admins group.



You may continue by clicking **Yes**. However keep in mind that in this case either the specified user must have administrative access to all remotely running DeviceLock Enterprise Servers or DeviceLock Certificate (the private key) must be installed on every computer with DeviceLock Enterprise Server.

If the user's account specified for the **This account** option does not have the Log On As A Service system privilege, the wizard automatically assigns it. This privilege is needed to start the service on behalf of the user.



If all of the service's startup parameters were specified correctly, the wizard starts DeviceLock Content Security Server.

Starting service
Please wait while the program is interacting with a service.
Starting service DLCSS on Local Computer
Cancel

It takes some time (up to a minute) before the DeviceLock Content Security Server service is started and the wizard's second page is displayed.

The second page of the wizard looks like this.

DeviceLock Content Security	y Server 🛛 🔀
Enable Default Security	
Users	1
Add Delete	2
NOTE: We strongly recomm	end that accounts in this list have local
administration privileges.	
Certificate Name:	
Certificate is not installed	<u>B</u> emove
	<back next=""> Cancel</back>

On this page, you define the list of users that have administrative access to DeviceLock Content Security Server and install DeviceLock Certificate (the private key).

### **Enable Default Security**

In the default security configuration all users with local administrator privileges (i.e. members of the local Administrators group) can connect to DeviceLock Content Security Server using a management console, change its settings and run search queries.

To turn on the default security, select the **Enable Default Security** check box.

If you need to define more granular access to DeviceLock Content Security Server, turn off the default security by clearing the **Enable Default Security** check box.

Then you need to specify authorized accounts (users and/or groups) that can connect to DeviceLock Content Security Server. To add a new user or group to the list of accounts, click **Add**. You can add several accounts simultaneously.

To delete a record from the list of accounts, use the **Delete** button. Using Ctrl and/or Shift you can highlight and remove several records simultaneously.

To define which actions are to be allowed for a user or user group, set the appropriate rights:

• **Full access** – to enable full access to DeviceLock Content Security Server. Users can change settings and run search queries.

- Change to enable change access to DeviceLock Content Security Server. Users can change settings, install/uninstall DeviceLock Content Security Server and run search queries, but they cannot add new users to the list of authorized accounts that can connect to DeviceLock Content Security Server or change access rights for existing users in this list.
- **Read-only** to enable read-only access to DeviceLock Content Security Server. Users can run search queries and view settings, but cannot modify anything or create a new index for Search Server.

**Note:** We strongly recommend that accounts included in this list have local administrator privileges because, in some instances, installing, updating and uninstalling the DeviceLock Content Security Server service may require access rights to Windows Service Control Manager (SCM) and shared network resources.

### **Certificate Name**

You may need to deploy the private key to DeviceLock Content Security Server if you want to enable authentication based on DeviceLock Certificate.

There are two methods of DeviceLock Content Security Server authentication on a remotely running DeviceLock Enterprise Server:

- User authentication the DeviceLock Content Security Server service is running under the user's account that has administrative access to DeviceLock Enterprise Server on the remote computer. For more information on how to run DeviceLock Content Security Server on behalf of the user, please read the description of the Log on as parameter.
- **DeviceLock Certificate authentication** in situations when the user under which DeviceLock Content Security Server is running cannot access DeviceLock Enterprise Server on the remote computer, you must authenticate based on a DeviceLock Certificate.

The same private key should be installed on DeviceLock Enterprise Server and on DeviceLock Content Security Server.

To install DeviceLock Certificate, click the ellipsis button —, and select the file with a private key. To remove DeviceLock Certificate, click **Remove**.

For more information regarding DeviceLock Certificate, see "DeviceLock Certificates."

Click **Next** to apply changes and proceed to the final page of the configuration wizard.

The final page of the wizard looks like this.

DeviceLock Content Sec	urity Server	×
License information:		
You have 0 valid license(s) in PLEASE REMEMBER THAT	istalled: THIS IS A 30-DAY TRIAL VERSION!	2
		9
Reset	Load License(	:)
	K Back Finish Cance	

On this page, you load your DeviceLock Content Security Server licenses.

#### License information

If you have purchased a license for Search Server, you should load this license into DeviceLock Content Security Server.

To load the license, click **Load License(s)** and select the license file. You can load several license files in series – one by one.

The trial period for DeviceLock Content Security Server is 30 days.

Click **Finish** to close the wizard and continue the installation process. Next, on the **Installation Wizard Completed** page, click **Finish** to complete the installation. On this page, you will have the option to go to the DeviceLock Content Security Server home page. This option is selected by default.

Note: To uninstall DeviceLock Content Security Server, do one of the following:

Use Add or Remove Programs in Control Panel to remove DeviceLock Content Security Server.

- OR -

Click **Start**, point to **All Programs**, point to **DeviceLock**, and then click **Remove DeviceLock Content Security Server**.

# **DeviceLock Certificates**

## **Overview**

DeviceLock Certificate is a cryptographic certificate that consists of two keys (the key pair): private and public:

• The private key must be stored on the administrator's computer and only the administrator must be able to access it. Also, the private key may be installed on DeviceLock Enterprise Server and DeviceLock Content Security Server.

**Note:** Make sure that non-administrative users can't get access to the private key.

• The public key is installed on every computer where DeviceLock Service is running. If the public key has not been preinstalled on the user's computer, there is no way to use the <u>Temporary White List</u> function or DeviceLock Certificate authentication on DeviceLock Enterprise Server.

## **Generating DeviceLock Certificates**

DeviceLock's Certificate Generation Tool allows you to generate DeviceLock Certificates.

We recommend that you generate only one DeviceLock Certificate and deploy its public key to all user computers. It is necessary to generate and install a new certificate only if the private key was either compromised (e.g. stolen) or lost.

To run the Certificate Generation Tool, select the **Certificate Generation Tool** item from the **File** menu in DeviceLock Enterprise Manager. To run the Certificate Generation Tool from DeviceLock Management Console (the MMC snap-in) and DeviceLock Group Policy Manager, use the context menu available by a right mouse click.

⇔ ⇒  [:	1 🗟 😰 📓 🖺	?	
🛃 Smartline 🛙	DeviceLock	Nam	9
🕒 🙆 Devi	Certificate Generation Tool.		wiceLock Service
🗄 🤕 Devi	DeviceLock Signing Tool About DeviceLock		wiceLock Enterprise Server
	View	•	
	Export List		
	Help		

The Certificate Generation Tool will run automatically when DeviceLock management consoles are installed on an administrator's computer that has no DeviceLock Certificate.

There are two simple steps to generate the key pair:

1. Define the name of the DeviceLock Certificate.



The Certificate Generation Tool auto-generates a name based on the current date and time, but you can type any other name.

2. Define the path and file names for private and public keys.



As soon as the DeviceLock Certificate is generated, you can start deploying the public key to users' computers.

**Note:** A newly generated DeviceLock Certificate does not automatically install on computers from the Certificate Generation Tool. You must deploy it manually from a DeviceLock management console.

## Installing/Removing DeviceLock Certificate

To install/remove the public key on/from user computers running DeviceLock Services, you can use any DeviceLock management console:

• DeviceLock Enterprise Manager

On the **Scan Network** dialog box, select the computers targeted for installation/removal of the public key and select the **Set Service Settings** plug-in.



Press the **Settings** button or double-click on the plug-in's record to open the configuration dialog box.

📾 Select Service Settings			X
Select DeviceLock Settings that should	apply to computer(s):		
Name	Created	Modified	Author
DL Settings 1	06/20/07 20:06:45	06/20/07 20:06:52	VM2000AD',Administrator
DL Settings 2	07/10/07 12:16:05	06/20/07 20:06:52	VM2000AD',Administrator
S Main DL Settings	07/10/07 12:16:14	06/20/07 20:06:52	VM2000AD\Administrator
🗹 🗊 Install Certificate	07/10/07 12:16:29	06/20/07 20:06:52	VM2000AD\Administrator
New Add E Copy Delete Re	dit		OK Cancel

Create the new XML file or use the existing one to define the policy needed to install/remove the certificate. Highlight the file in the list and then press the **Edit** button to modify the policy as described in the <u>next section (below)</u>. When finished modifying the policy, select its file by enabling the checkmark next to the file's name in the list.

Press the **OK** button to close the configuration dialog box and then press the **Scan** button on the **Scan Network** dialog box to start the DeviceLock Certificate installation/removal process.

• DeviceLock Management Console, DeviceLock Group Policy Manager and DeviceLock Service Settings Editor

If you are using DeviceLock Management Console (the MMC snap-in), first you need to connect it to the computer running DeviceLock Service. Use the context menu available by a right mouse click.



When DeviceLock Group Policy Manager is used, you don't need to connect to any computer since it connects to the Group Policy Object. Also, you don't need to connect to the computer when modifying the policy in the XML file using DeviceLock Service Settings Editor.

Activate the Service Options item.

⇔ ⇒ € 🛛 🖧 🔮		
Smartline DeviceLock	Name	State
E- 🙀 DeviceLock Service	DeviceLock Administrators	Disabled
E Service Options	2 Shadowing	
DeviceLock Administrators	USB/FireWire blocked message	Disabled
- 10 Shadowing	Expired message	Disabled
Devices	DeviceLock Enterprise Server(s)	xpvirt
Audit Log Viewer	Log policy changes and Start/Stop events	Enabled
Devicel ock Enterprice Server	DeviceLock certificate	DeviceLock Certificate [05/11/2006
Concerce and hise server	SUse Group Policy	Disabled

Double-click the **DeviceLock certificate** parameter to open the configuration dialog box.

DeviceLock Certificate	? 🔀
Computer Name: Local Computer Certificate Name:	
DeviceLock Certificate [05/11/2006 01:28:52 P	PM]
	. <u>Kemove</u>
OK	Cancel

Specify the path to the public key in the **Certificate Name** parameter if you want to install the certificate. You can use the ... button to select the file with a public key.

To remove the public key, use the **Remove** button.

Press the **OK** button to close the configuration dialog box and apply changes.

To install/remove the private key on/from DeviceLock Enterprise Server and DeviceLock Content Security Server, you can use DeviceLock Management Console (the MMC snap-in).

You need to connect DeviceLock Management Console to the computer running DeviceLock Enterprise Server or DeviceLock Content Security Server. Use the context menu available by a right mouse click.



Activate the Server Options item.

⇔ ⇒ 🗈 📧 🗟 😫		
🛃 Smartline DeviceLock	Name	State
🗈 🙀 DeviceLock Service	Server Administrators	Enabled
DeviceLock Enterprise Server	DeviceLock certificate	DeviceLock Certificate [05/11/
Server Options	Service startup account	LocalSystem
Shadow Log Viewer	- Le port	Dynamic
	🗗 Database name	DevicelockDB6
	, Connection type	ODBC Driver
	SQL Server name	VM2000SERVER\VMINSTANCE
	📴 SQL Server Login	sa
	💂 Store path	%systemroot%\dlstore
	Store shadow files in SQL Server	Disabled
	DeviceLock license(s)	Trial mode

Double-click the **DeviceLock certificate** parameter to open the configuration dialog box.

DeviceLock Enterprise Server	
Enable Default Security	
Users	
√M2000AD \D omain Admins	Full access
1 VM2000AD \Test	Read-only
2 Administrators	Full access
Add Delete Full access            Add         Delete         Full access           MOTE: We strongly recommend that accounts in this list h administrator privileges.	ave local
Certificate Name:	
DeviceLock Certificate [05/11/2006 01:28:52 PM]	Remove
OK	Cancel

Specify the path to the private key in the **Certificate Name** parameter if you want to install the certificate. You can use the ... button to select the file with a private key.

To remove the private key, use the **Remove** button.

Press the **OK** button to close the configuration dialog box and apply changes.

For more information regarding installing the private key on DeviceLock Enterprise Server and DeviceLock Content Security Server, please read <u>Installing DeviceLock</u> Enterprise Server and Installing DeviceLock Content Security Server sections of this manual.

# **DeviceLock Signing Tool**

## **Overview**

The DeviceLock Signing Tool is used to grant users temporary access to requested devices and sign XML files containing DeviceLock Service settings exported from DeviceLock Management Console or DeviceLock Group Policy Manager.

To run the DeviceLock Signing Tool, select **DeviceLock Signing Tool** from the **File** menu in DeviceLock Enterprise Manager or from the context menu in DeviceLock Management Console (the MMC snap-in), DeviceLock Group Policy Manager or DeviceLock Service Settings Editor.

A DeviceLock Signing Tool		×
Certificate Name:	DeviceLock Certificate [05/11/2006 01:28:52 PM]	New

First of all you should load the corresponding DeviceLock Certificate (the private key).

The DeviceLock Signing Tool must use the private key that belongs to the same certificate as the public key installed on the user's computer.

By default, the DeviceLock Signing Tool automatically loads the last certificate used. You can load another certificate by pressing the ... button and selecting a file with the private key.

To generate the new certificate you can run the <u>Certificate Generation Tool</u> directly from the DeviceLock Signing Tool. To do so, you should press the **New** button. However, please keep in mind that if you generate a new certificate and intend to use its new private key in the DeviceLock Signing Tool, you must also deploy the corresponding public key on the user's computer.

Then, decide what action you want to perform: <u>generate an Unlock Code</u> or <u>sign an</u> <u>XML file</u> containing DeviceLock Service settings.

## **Device Code**

To grant the user temporary access to a requested device you should generate an Unlock Code upon receiving the Device Code from this user.

For more information on using temporary white list, please read the <u>Temporary</u> <u>White List</u> section of this manual.

A DeviceLock Si	gning Tool
Certificate Name:	DeviceLock Certificate [05/11/2006 01:28:52 PM] New
Device Code Se	rvice Settings
Device Code :	H64KQ - EMNC2 - HLDV - JP3I - DSSD - HPEU
Device Class :	Disk drives (Unique)
Allowed Period:	1 day
Generate	Unlock Code : LMVDK-720NU-1A000-R1LJN-KQJCQ-50D0R-605VA
	Close

There are four simple steps to generating an Unlock Code for the user:

- 1. Load the corresponding DeviceLock Certificate (see above)
- 2. Enter the Device Code, the user provides to you.

As soon as the correct Device Code is entered, you can see the class of the device the user wants access to in the **Device Class** field. The device class information helps you to control what kind of device the user is going to use. If, for example, a user tells the administrator that he/she is going to use a USB scanner but actually is trying to obtain access to a USB flash drive, the administrator would recognize the discrepancy.

There is also a field (in round brackets) showing whether the requested device can be authorized as a unique device (**Unique**) or can be authorized only as a model (**Model**), i.e. whether or not it has a serial number. If you authorize the device as a model, then the user is granted access to all devices of this model. For more information on this, please read the <u>USB Devices</u> <u>White List</u> section of this manual.

 Select the period when the requested device will be allowed. In Allowed Period, you can select several predefined periods: 5, 15, 30, 60 minutes, 5 hours, 1 or 2 days, 1 or 2 weeks, 1 month, until the device is unplugged or until the user is logged off.

When you select a fixed time period (e.g. 10 minutes), the user is granted access to the requested device for only this period. As soon as the allowed time expires, access to the device is denied again. It doesn't matter what the user is doing with this device – even if he/she is still copying files onto the USB disk or printing a document on the USB printer, all operations will be aborted.

To allow the user to use a requested device without any time limitations, select until unplug in **Allowed Period**. The user is then granted access to the

device while it is plugged into the port. As soon as the user unplugs this device, access to it is denied again.

4. Press the **Generate** button to create an Unlock Code. Provide this code to the user over the phone or in any other suitable way.

The process of generating an Unlock Code can be a time-consuming operation. It depends on your computer's processing speed and could take as long as several seconds.

## **Service Settings**

To avoid unauthorized modification you can sign an XML file containing DeviceLock Service settings exported from DeviceLock Management Console or DeviceLock Group Policy Manager or created using DeviceLock Service Settings Editor.

Later this file can be sent to users whose computers are not online and thus out-ofreach via management consoles.

DeviceLock Si	igning Tool			X
Certificate Name:	DeviceLo	:k Certificate [05/1	1/2006 01:28:52 PM]	New
Device Code Se	rvice Settings			
Unsigned file:	C:\exchange\tes	t.xml		
Signed file:	C:\exchange\tes	t_signed.xml		
Valid until	21.60 DM		Only for computer(s)	
11/30/2007 12:	21:59 PM		Appare	
Sign				
				Close

There are six simple steps to signing an XML file:

- 1. Load the corresponding DeviceLock Certificate (see above)
- 2. Load the file with DeviceLock Service settings you need to sign.

The full path to this file must be specified in the **Unsigned file** field. You can use the ... button to select the file.

The XML file with DeviceLock Service settings can be created using **Save Service Settings** from the context menu in DeviceLock Management Console, DeviceLock Group Policy Manager or DeviceLock Service Settings Editor.

- 3. In the **Signed file** field, specify the resultant file. You can use the ... button to select the folder where this file will be created.
- 4. Decide whether the resultant file should contain expiration information or not.

If you want to allow users to import settings from this file without any time limitations, disable the **Valid until** flag.

If you enable the **Valid until** flag and specify the date/time, then the expiration information writes to the resultant file and users can import settings from this file only before the specified date/time.

Please note that this parameter affects only users that are trying to import DeviceLock Service settings via the DeviceLock applet from the Windows Control Panel. When an XML file with settings is loaded using **Load Service Settings** from the context menu in DeviceLock Management Console or DeviceLock Group Policy Manager, the expiration information (if any) is ignored.

5. Decide whether the resultant file can be used only on specific computers or not.

If you want to allow users to import settings from this file on any computers, disable the **Only for computer(s)** flag.

If you enable the **Only for computer(s)** flag and specify the computer name then users will be able to import settings from this file only on this specified computer. Using the semicolon (;) as a separator, you can specify several computer names such that the resultant file can be used on any of these computers.

**Note:** You can't use the computer's IP address in this parameter. You must specify the computer name exactly as it is displayed in the System applet from the Windows Control Panel.

You can also load a predefined list of computers from the external text file. To open an external file, press the ... button. This text file must contain each computer's name on separate lines.

Please note that this parameter affects only users that are trying to import DeviceLock Service settings via the **DeviceLock** applet from the Windows Control Panel. When an XML file with settings is loaded using **Load Service Settings** from the context menu in DeviceLock Management Console or DeviceLock Group Policy Manager, the computer's name information is ignored.

6. Press the **Sign** button to create a signed file with DeviceLock Service settings. Provide this file to the user in any suitable way.

The process of file signing can be a time-consuming operation. It depends on your computer's processing speed and could take as long as several seconds.

When the user wants to apply DeviceLock Service settings from this signed file, he/she should run the **DeviceLock** applet from the Control Panel and select the **Import Service Settings** option.



**Note:** On Windows XP and later, the user must switch the Control Panel to Classic View in order to view all available applets.

DeviceLock	
	This tool allows you to obtain temporary access to a device and load the signed file with new settings.
	<ul> <li>Temporary White List Authorization Tool</li> <li>Import Service Settings</li> </ul>
	Click 'Next' below to begin.
	< Back Next> Cancel

There are two simple steps for the user to import DeviceLock Service settings from the signed file:

1. In the **Signed file** field, specify the full path to this signed file. Use the ... button to select the file.

😫 Import (	DeviceLock Service Settings	×
Select a sign	ed file with DeviceLock Service Settings provided by the Administrator:	
Signed file:	C:\exchange\dl\Service Settings_signed.xml	
		_
	< Back Finish Cance	

2. Press the **Finish** button. If the digital signature in the file is valid, then the new settings will be applied to DeviceLock Service immediately.

Import DeviceLock Service Settings	×
File has been successfuly loaded.	
ОК	

The user can also load the signed file with DeviceLock Service settings using the command line:

### **DLTempAccess.cpl -s** <path to signed file>

where *<path to signed file>* is the path to the signed file with DeviceLock Service settings. For example:

### DLTempAccess.cpl -s "C:\Program Files\DeviceLock\settings\_signed.dls"

All successful attempts to load settings are logged, if logging of changes is enabled in the <u>Service Options</u>.

# **DeviceLock Management Console**

## Overview

DeviceLock Management Console is a snap-in for Microsoft Management Console (MMC).

Using DeviceLock Management Console, you can view and change permissions and audit rules, install and update DeviceLock Service as well as view audit records for individual computers.

Also, DeviceLock Management Console is used for viewing logs stored on DeviceLock Enterprise Server, running search queries on DeviceLock Content Security Server and for managing these servers.

DeviceLock Management Console should be used on the computer from which the administrator is managing DeviceLock Services, DeviceLock Enterprise Servers and DeviceLock Content Security Servers on the network.

For information on how to install DeviceLock Management Console, please read the <u>Installing Management Consoles</u> section of this manual.

To run DeviceLock Management Console, select the appropriate shortcut from the **Programs** menu available by clicking the Windows **Start** button.



Alternatively, you can start MMC and add the DeviceLock Management Console snapin manually:

- 1. Run **mmc** from the command line or use the **Run** menu to execute this command.
- 2. Open the **File** menu, and then click **Add/Remove snap-in**.

6	Console1 - [	Conso	le Root]			
Ĩ	Ele Action	⊻iew	Favorites	₩indow	Help	_ & ×
	New Open Save Save As Options 1 C:\downlo 2 C:\WINDO 3 DeviceLoo 4 DeviceLoo Exit	e Snap-i bads\Gro DWS\\ k Manag k Manag	n up Policy.msi comprigmt.m jement.msc jement.msc	Ctrl+N Ctrl+O Ctrl+S Ctrl+M		Name There are no items to show in this view.
Adds	or removes inc	fividual s	nap-ins.			

3. Click the **Standalone** tab, and then click **Add**.

Add/Remove Snap-i	in	? 🗙
Standalone Extensio	ns or remove a standalone Snap-in from the c	onsole.
Snap-ins added to:	Console Root	
Description		
Add	Remove About	
	ОК	Cancel

4. Select **DeviceLock Management Console** from the list, then click **Add**.

Add Standalone Snap-in	?	
Available Standalone Snap-ins:		
Snap-in	Vendor	^
g≜ActiveX Control	Microsoft Corporation	
Certificates	Microsoft Corporation	=
Component Services	Microsoft Corporation	
E Computer Management	Microsoft Corporation	
B Device Manager	Microsoft Corporation	
DeviceLock Management Console	SmartLine Inc	
September 2015 Defragmenter	Microsoft Corp, Executi	
🗃 Disk Management	Microsoft and VERITAS	
Event Viewer	Microsoft Corporation	
- Folder	Microsoft Corporation	~
Description This snap-in allows you to configure Devic	ceLock settings.	
	Add Close	

## Interface

DeviceLock Management Console has a user-friendly, easy-to-use standard interface provided by Microsoft Management Console (MMC). At any time, you can press the F1 key to get context-specific help.



DeviceLock Management Console consists of a window divided into two panes. The left pane contains the console tree; the right pane contains details. When you select an item in the console tree, information about that item is displayed in the details pane.

There are three independent parts in DeviceLock Management Console:

- 1. **DeviceLock Service** allows you to connect to and manage DeviceLock Services running on remote and local computers.
- 2. **DeviceLock Enterprise Server** allows you to connect to and manage DeviceLock Enterprise Servers running on remote and local computers.
- DeviceLock Content Security Server allows you to connect to and manage DeviceLock Content Security Servers running on remote and local computers.

## **Connecting to Computers**

First of all, you should connect to the computer where DeviceLock Service, or DeviceLock Enterprise Server, or DeviceLock Content Security Server is running. Use the context menu **Connect** item or the appropriate button on the toolbar.



You can simultaneously connect to DeviceLock Service, DeviceLock Enterprise Server and DeviceLock Content Security Server even if they are running on different computers.

Select Computer			? 🛛
DeviceLock Management     C Local computer: (the	Console will manage:	3 on)	
Another computer:	WWM2000SERVER	•	Browse
		ОК	Cancel

Specify the remote computer name or IP address you want to connect to in the **Another computer** parameter. To browse for available computers in your network, use the **Browse** button.

To connect DeviceLock Management Console to the computer where DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server was configured using a fixed port, you should specify this port in square brackets next to the computer name, e.g. \\computer\_name[port number].

To connect to the local computer, use the **Local computer** option.

Press the **OK** button to connect to the selected computer.

**Note:** Make sure that the remote computer you've selected to connect to is accessible from the computer where DeviceLock Management Console is running. The remote computer must work under a DeviceLock-compatible OS (Windows NT 4.0 SP6 and later). It must have a functioning TCP/IP protocol. In case a firewall (including built-in Windows Firewall) is installed on the remote computer, it must be <u>properly configured</u> to allow connection with DeviceLock Service, DeviceLock Enterprise Server and/or DeviceLock Content Security Server.

DeviceLock Service automatically adds itself to the exception list of Windows Firewall.

When you're trying to connect to DeviceLock Service on a computer where it is not installed or is outdated, DeviceLock Management Console suggests that you install or update the service. For more information regarding the remote service deployment, please read the <u>Remote Installation via DeviceLock Management Console</u> section of this manual.

You receive the warning message when you connect to DeviceLock Service configured to work in the Group Policy mode.



If you change some parameter using DeviceLock Management Console, it will revert to its original state (defined in GPO) on the next Group Policy update. For more information, please read the <u>Service Options</u> section of this manual.

If you're trying to connect to DeviceLock Enterprise Server or DeviceLock Content Security Server on a computer where it is not installed or stopped, you receive a connection error.



DeviceLock Enterprise Server and DeviceLock Content Security Server must be installed and started before DeviceLock Management Console can connect to them. For more information regarding the servers deployment, please read the <u>Installing</u> <u>DeviceLock Enterprise Server</u> and <u>Installing DeviceLock Content Security Server</u> sections of this manual.

If you don't have administrative privileges on the selected computer, DeviceLock Management Console suggests that you connect under the account of another user.

Enter Netwo	rk Password	? 🛛
Incorrect pass vm2000se	sword or unknown username for: erver	Cancel
Connect As:	vm2000ad\administrator	
Password:	*****	

In the **Connect As** parameter you can specify a user account with administrative privileges. This account should also be on the list of DeviceLock Administrators in case this administrator safeguard feature is enabled for DeviceLock Service or DeviceLock Enterprise Server or DeviceLock Content Security Server.

A "credentials conflict" can result if, after connecting to (i.e., you have a mapped network disk, opened shared resource, etc.) a selected computer under a user that can't access DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server, you then try to login as another user in DeviceLock Management Console. To avoid this conflict you must first delete your existing connection.

When DeviceLock Management Console detects a credentials conflict it displays a list of existing connections on your local computer and suggests that you delete some of them.

al Co e crec	onnections dentials supplied conflict with ar	existing set of cre	dentials (User: TestAdmin
main: u mus	VM2000AD). To establish a con it disconnect the existing conne Remote	ctions to vm2000se	erent set of credentials, r erver.
0car De	Num2000cerver\IDC\$	OK	testadmin

Highlight all existing connections to the computer you want to connect to and press the **Disconnect** button.

Press the **Close** button and then try to connect to this computer again.

**Note:** Sometimes the existing connection can't be terminated thus preventing you from connecting under a different user account in DeviceLock Management Console. In this case you need to run DeviceLock Management Console under a user that either has sufficient privileges to access DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server or has no connections to the selected computer at all. You may use the Run As function (run RUNAS from the command line) available in Windows 2000 and later to run DeviceLock Management Console under another user.

### **Possible Connection Errors**

When you're trying to connect to a computer with DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server you may receive some of these errors:

(1722) The RPC server is unavailable – you're trying to connect to a computer that either does not exist (the wrong name or IP address) or is not accessible. Make sure that the computer name you've specified is correct. Try to ping this computer by its name and IP address and connect to it using any standard Windows administrative tool (such as Computer Management, Services and so on). Make sure that this computer is working under a DeviceLock-compatible OS (Windows NT 4.0 and later).

Also, it is possible that a firewall is blocking access to this computer. You would need to configure your firewall to allow some ports needed for DeviceLock. You could also instruct DeviceLock to use the fixed TCP port, making it easier to configure a firewall. By default, DeviceLock Service,

DeviceLock Enterprise Server and DeviceLock Content Security Server are using 9132, 9133 and 9134 ports thereafter. For more information, please refer to the <u>Frequently Asked Questions</u> section of our Web site. Also, please note that DeviceLock Service automatically adds itself to the exception list of Windows Firewall.

 (1753) There are no more endpoints available from the endpoint mapper – you're trying to connect to a computer where DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server is not accessible. First of all, make sure that DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server is installed and started on the remote computer.

It is possible that this computer was just booted and Windows is still initializing its services. The Remote Procedure Call (RPC) service may not be running yet.

Also, a firewall could be blocking access to DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server. For more information, please read the above description of the 1722 error.

To troubleshoot RPC Endpoint Mapper errors, please read this Microsoft article: <u>support.microsoft.com/kb/839880/en-us</u>

• **(5)** Access is denied – you don't have enough privileges on the remote computer. Make sure that DeviceLock Management Console is trying to connect to the remote computer under a user with local administrator privileges on that computer.

You may also need to run DeviceLock Management Console under a different user that can authenticate on the remote computer as a local admin.

 (7045) You must have administrative privileges to perform this operation – you don't have sufficient privileges to access DeviceLock Service, DeviceLock Enterprise Server or DeviceLock Content Security Server because the user is not in the list of DeviceLock Administrators. Make sure that DeviceLock Management Console is trying to connect to the remote computer under the user that is in the list of DeviceLock Administrators on that computer.

## Managing DeviceLock Service

Expand the **DeviceLock Service** item to access all of the service function and configuration parameters.

SeviceLock Managem	ent Console	
<u>File Action View Help</u>		
	? 🗉 💻 🚮 📓 😫 ?	
DeviceLock	Service Options	
Service Options     Devices     Service Options     Audit Log Viewe     Shadow Log View     DeviceLock Enterpris	Connect Reconnect Connect to Local Computer at Startup Load Service Settings Save Service Settings Save & Sign Service Settings Create MSI Package Certificate Generation Tool DeviceLock Signing Tool About DeviceLock	
-	View	
-	Help	
Connects to a different comput	er	

There is a context menu available via a right mouse click on the **DeviceLock Service** item:

- **Connect** connects to any computer that you specify. For more information please read the <u>Connecting to Computers</u> section of this manual.
- **Reconnect** connects to the currently connected computer once again.
- **Connect to Local Computer at Startup** check this flag to instruct DeviceLock Management Console to automatically connect to the local computer each time it starts up.
- Load Service Settings loads previously saved settings from the XML file and applies these settings to the currently connected DeviceLock Service. You need to select the file that was created either by DeviceLock Service Settings Editor, DeviceLock Management Console or DeviceLock Group Policy Manager. Since the signature is not validated at this step, it can be either a signed or non-signed file.
- Save Service Settings exports all settings from the currently connected DeviceLock Service to an external XML file. Later this file can be modified using DeviceLock Service Settings Editor and loaded via DeviceLock Management Console and/or DeviceLock Group Policy Manager. Also, this file can be sent to users whose computers are not online and thus out-of-reach via management consoles. To avoid unauthorized modification the file should be signed with the DeviceLock Certificate (the private key) using the DeviceLock Signing Tool.
- Save & Sign Service Settings exports all settings from the currently connected DeviceLock Service to an external XML file and automatically signs it with the most recent DeviceLock Certificate (the private key). This menu

item is disabled when the DeviceLock Signing Tool has no previously loaded private key.

- Certificate Generation Tool runs the special tool that allows you to generate DeviceLock Certificates. For more information please read the <u>Generating DeviceLock Certificates</u> section of this manual.
- Create MSI Package creates the custom Microsoft Software Installer (MSI) package with settings from the currently connected DeviceLock Service. At the first step you need to select the source MSI package with DeviceLock Service. You may use MSI packages that ship with DeviceLock (such as DeviceLock Service.msi and DeviceLock Service x64.msi).

Then you need to specify the name of the resultant (target) MSI package that will be generated based on the source MSI package (specified at the first step) and settings from the currently connected DeviceLock Service.

Later this custom MSI package can be used to deploy DeviceLock Service instances across the network with predefined policies. For more information on how to deploy DeviceLock Service using MSI, please read the <u>Installation</u> via Group Policy section of this manual.

**Note:** If you use a custom MSI package with defined DeviceLock Service settings to deploy DeviceLock Service using Group Policy, these settings are not applied to client computers if any one of the following conditions is true:

- The default security is disabled on remotely running DeviceLock Services.

- The GPO applied to client computers has the **Override Local Policy** setting enabled.

Please note that the **Create MSI Package** menu item is disabled when there is no Microsoft Windows Installer (version 1.0 or later) installed on the local computer.

- DeviceLock Signing Tool runs the special tool that allows you to grant users temporary access to requested devices and sign XML files with DeviceLock Service settings. For more information please read the <u>DeviceLock</u> <u>Signing Tool</u> section of this manual.
- About DeviceLock displays a dialog box with information about the DeviceLock version and your licenses.

### Service Options

These additional parameters allow you to tune up the DeviceLock Service configuration. Use the context menu available by a right mouse click on every parameter.

e and the second s			
File Action View Help			
SeviceLock	Name	State	
DeviceLock Service (Local, WINXPPRC     Service Options     Service Options     DeviceLock Administrators     Off Auditing & Shadowing	DeviceLock Administrators     Auditing & Shadowing     Auditing & Shadowing     Anti-keylogger     Benervetion	Disabled	
Anti-keylogger	USB/FireWire blocked message	Disabled	
Encryption	Expired message	Disabled	
Devices	Content-Aware blocked read message	Disabled	
Audit Log Verwer	Content-Aware blocked write message	Enabled	
R Shadow Log Viewer	Protocols blocked message	Enabled	
E DeviceLock Enterprise Server (Local, \     DeviceLock Content Security Server	Content verification message DeviceLock Enterprise Server(s)	Enabled	
	Log policy changes and Start/Stop events	Enabled	
	SUse Group Policy	Disabled	
	Sector Fast servers first	Disabled	
	🔔 Traffic priority	High	
	Always show tray icon	Disabled	
	Archives content inspection on read	Enabled	
-	Archives content inspection on write	Enabled	
< >	2 Offline mode detection	Wired Connectivity	
Local Policy is enabled for this machine (Regular	Profile).	Local Computer	

### USB/FireWire blocked message

You can define a custom message to be displayed to users when access to a USB or FireWire device is denied at the interface (USB or FireWire) level or type (Removable, CD/DVD, etc.) level.

Blocked Message	? 🗙
Computer Name: xpvirt	
✓ Enable USB/FireWire Blocked Message	
Blocked Message Caption:	
DeviceLock Security Subsystem	
Blocked Message Text:	
You do not have permissions to access "%DEVICE% %DRIVE%". Please contact your system administrator.	< N
Restore Defaults	
OK Ca	ancel

To enable this custom message, select the **Enable USB/FireWire Blocked Message** check box.

Also, you can define additional parameters, such as:

- **Blocked Message Caption** the text to be displayed as a caption. You can use three predefined macros within the text:
  - **%TYPE%** inserts the port name (USB port, FireWire port) where the device is plugged.
  - **%DEVICE%** inserts the name of the device (e.g. USB Mass Storage Device) received from the system.
  - **%DRIVE%** inserts the drive letter of the storage device (e.g. F:). If the device doesn't have a letter, then this macro inserts an empty string.

Using these macros you can create more informative messages for users.

• **Blocked Message Text** – the main text of the message. You can use the predefined macros described above within the text.

### **Expired message**

You can define a custom message to be displayed to users when the allowed period for temporary white listed devices is expired and devices have been removed from <u>Temporary White List</u>.

🗈 Expired message 🛛 💽	
Computer Name: xpvirt	
✓ Enable Expired Message	
Expired Message Caption:	
DeviceLock Security Subsystem	
Expired Message Text:	
The allowed period for "%DEVICE% %DRIVE%" is expired. The device has been removed from Temporary White List.	
Restore Defaults	
OK Cance	

To enable this custom message, select the **Enable Expired Message** check box.

Also, you can define additional parameters, such as:

- **Expired Message Caption** the text to be displayed as a caption. You can use two predefined macros within the text:
  - **%DEVICE%** inserts the name of the device (e.g. USB Mass Storage Device) received from the system.

• **%DRIVE%** – inserts the drive letter of the storage device (e.g. F:). If the device doesn't have a letter, then this macro inserts an empty string.

Using these macros you can create more informative messages for users.

• **Expired Message Text** – the main text of the message. You can use the predefined macros described above within the text.

#### **Content-Aware Blocked Read Message**

You can define a Content-Aware blocked read message (notification balloon) to be displayed to users when they try to read a file to which they are denied access. This message balloon is shown in the notification area of the taskbar on client computers. By default, DeviceLock does not display the Content-Aware blocked read message.

To enable or disable the Content-Aware blocked read message, right-click **Content-Aware blocked read message** and then click **Properties**, or double-click **Content-Aware blocked read message**.

🛾 Content-Aware blocked read message 👘 🛛 💽
Computer Name: Local Computer
Enable Content-Aware Blocked Message
Blocked Message ⊆aption:
DeviceLock Security Subsystem
Blocked Message Text:
You do not have permissions to read %FILENAME%. Please contact your system administrator.
Restore Defaults
OK Cancel

In the **Content-Aware blocked read message** dialog box, do the following:

USE THIS	TO DO THIS
Enable Content- Aware Blocked	Enable or disable the display of the Content-Aware blocked read message.
Message	Select the <b>Enable Content-Aware Blocked Message</b> check box to enable the display of the message.
	Clear the Enable Content-Aware Blocked Message check box to

USE THIS	TO DO THIS
	disable the display of the message.
Blocked Message Caption	Specify the text to display in the title bar of the message balloon. By default, the Blocked Message Caption text is as follows: <b>DeviceLock Security Subsystem</b>
Blocked Message Text	Specify the text to display in the message balloon. By default, the Blocked Message Text for the Content-Aware blocked read message is as follows: You do not have permissions to read %FILENAME%. Please contact your system administrator. where %FILENAME% is the path and file name of the file to be inserted.
Restore Defaults	Restore the default settings.

For a detailed description of the Content-Aware Rules feature, see "<u>Content-Aware</u> <u>Rules for Devices (Regular Profile)</u>" and "<u>Content-Aware Rules for Protocols (Regular</u> <u>Profile)</u>."

### **Content-Aware Blocked Write Message**

You can define a Content-Aware blocked write message (notification balloon) to be displayed to users when they try to write a file to which they are denied access. This message balloon is shown in the notification area of the taskbar on client computers. By default, DeviceLock displays the Content-Aware blocked write message.

To enable or disable the Content-Aware blocked write message, right-click **Content-Aware blocked write message** and then click **Properties**, or double-click **Content-Aware blocked write message**.

📓 Content-Aware blocked write message 👘 😰 🔀
Computer Name: Local Computer
Enable Content-Aware Blocked Message
Blocked Message Caption:
DeviceLock Security Subsystem
Blocked Message Text:
You do not have permissions to write %FILENAME%. Please contact your system administrator.
Restore Defaults
OK Cancel

In the **Content-Aware blocked write message** dialog box, do the following:

Enable Content- Aware Blocked MessageEnable or disable the display of the Content-Aware blocked write message.Select the Enable Content-Aware Blocked Message check box to enable the display of the message.Clear the Enable Content-Aware Blocked Message check box to disable the display of the message.Blocked Message CaptionSpecify the text to display in the title bar of the message balloon. By default, the Blocked Message Caption text is as follows: DeviceLock Security SubsystemBlocked Message TextSpecify the text to display in the message balloon. By default, the Blocked Message Text for the Content-Aware blocked write message is as follows: You do not have permissions to write %FILENAME%. Please contact your system administrator. where %FILENAME% is the path and file name of the file to be inserted.	USE THIS	TO DO THIS
MessageSelect the Enable Content-Aware Blocked Message check box to enable the display of the message.Clear the Enable Content-Aware Blocked Message check box to disable the display of the message.Blocked Message CaptionSpecify the text to display in the title bar of the message balloon. By default, the Blocked Message Caption text is as follows: DeviceLock Security SubsystemBlocked Message TextSpecify the text to display in the message balloon. By default, the Blocked Message Text for the Content-Aware blocked write message is as follows: You do not have permissions to write %FILENAME%. Please contact your system administrator. where %FILENAME% is the path and file name of the file to be inserted.Pastore DefaultsRestore the default settings	Enable Content- Aware Blocked Message	Enable or disable the display of the Content-Aware blocked write message.
Clear the Enable Content-Aware Blocked Message check box to disable the display of the message.         Blocked Message Caption       Specify the text to display in the title bar of the message balloon. By default, the Blocked Message Caption text is as follows:         DeviceLock Security Subsystem         Blocked Message Text       Specify the text to display in the message balloon. By default, the Blocked Message Text for the Content-Aware blocked write message is as follows:         You do not have permissions to write %FILENAME%. Please contact your system administrator.         Where %FILENAME% is the path and file name of the file to be inserted.		Select the <b>Enable Content-Aware Blocked Message</b> check box to enable the display of the message.
Blocked Message Caption       Specify the text to display in the title bar of the message balloon. By default, the Blocked Message Caption text is as follows:         DeviceLock Security Subsystem         Blocked Message Text       Specify the text to display in the message balloon. By default, the Blocked Message Text for the Content-Aware blocked write message is as follows:         You do not have permissions to write %FILENAME%. Please contact your system administrator. where %FILENAME% is the path and file name of the file to be inserted.		Clear the <b>Enable Content-Aware Blocked Message</b> check box to disable the display of the message.
Caption       By default, the Blocked Message Caption text is as follows:         DeviceLock Security Subsystem         Blocked Message       Specify the text to display in the message balloon.         By default, the Blocked Message Text for the Content-Aware blocked write message is as follows:       You do not have permissions to write %FILENAME%. Please contact your system administrator.         Where %FILENAME% is the path and file name of the file to be inserted.       Pestore Defaults	Blocked Message	Specify the text to display in the title bar of the message balloon.
DeviceLock Security Subsystem         Blocked Message Text       Specify the text to display in the message balloon.         By default, the Blocked Message Text for the Content-Aware blocked write message is as follows:         You do not have permissions to write %FILENAME%. Please contact your system administrator.         where %FILENAME% is the path and file name of the file to be inserted.         Pestore Defaults       Pestore the default settings	Caption	By default, the Blocked Message Caption text is as follows:
Blocked Message       Specify the text to display in the message balloon.         By default, the Blocked Message Text for the Content-Aware blocked write message is as follows:         You do not have permissions to write %FILENAME%. Please contact your system administrator.         where %FILENAME% is the path and file name of the file to be inserted.         Pestore Defaults       Pestore the default settings		DeviceLock Security Subsystem
Text       By default, the Blocked Message Text for the Content-Aware blocked write message is as follows:         You do not have permissions to write %FILENAME%. Please contact your system administrator.         where %FILENAME% is the path and file name of the file to be inserted.         Pestore Defaults       Restore the default settings	Blocked Message Text	Specify the text to display in the message balloon.
You do not have permissions to write %FILENAME%. Please contact your system administrator.         where %FILENAME% is the path and file name of the file to be inserted.         Pestore Defaults       Restore the default settings		By default, the Blocked Message Text for the Content-Aware blocked write message is as follows:
where <b>%FILENAME%</b> is the path and file name of the file to be inserted.		You do not have permissions to write %FILENAME%. Please contact your system administrator.
Pestore Defaults		where <b>%FILENAME%</b> is the path and file name of the file to be inserted.
Restore Defaults Restore the default settings.	<b>Restore Defaults</b>	Restore the default settings.

For a detailed description of the Content-Aware Rules feature, see "<u>Content-Aware</u> <u>Rules for Devices (Regular Profile)</u>" and "<u>Content-Aware Rules for Protocols (Regular</u> <u>Profile)</u>."

### Protocols blocked message

You can define a Protocols blocked message (notification balloon) to be displayed to users when they try to access a protocol to which they are denied access. This message balloon is shown in the notification area of the taskbar on client computers.

To enable or disable the Protocols blocked message, right-click **Protocols blocked message**, and then click **Properties**, or double-click **Protocols blocked message**.

Protocols blocked message
Computer Name: Local Computer
Enable Protocols Blocked Message
Blocked Message Caption:
DeviceLock Security Subsystem
Blocked Message Text:
You do not have permissions to access "%PROTOCOL%". Please contact your system administrator.
Restore Defaults
OK Cancel

In the **Protocols blocked message** dialog box, do the following:

USE THIS	TO DO THIS
Enable Protocols Blocked Message	Enable or disable the display of the Protocols blocked message.
	Select the <b>Enable Protocols Blocked Message</b> check box to enable the display of the message.
	Clear the <b>Enable Protocols Blocked Message</b> check box to disable the display of the message.
Blocked Message Caption	Specify the text to display in the title bar of the message balloon.
	By default, the Blocked Message Caption text is as follows:
	DeviceLock Security Subsystem
Blocked Message Text	Specify the text to display in the message balloon.
	By default, the Blocked Message Text is as follows:
	You do not have permissions to access %PROTOCOL%. Please contact your system administrator.
	where <b>%PROTOCOL%</b> is the name of the protocol to be inserted.
<b>Restore Defaults</b>	Restore the default settings.

For a detailed description of the Protocols feature, see "Protocols (Regular Profile)."

### Content verification message

Checking the content of files copied to devices or transmitted over the network can be a time-consuming operation. You can define a Content verification message to be displayed to users when content inspection is in progress. This message is displayed 20 seconds after DeviceLock Service starts checking the file content.

To enable or disable the Content verification message, right-click **Content verification message**, and then click **Properties**, or double-click **Content verification message**.

Content verification message
Computer Name: Local Computer
Enable Content Verification Message
Content Verification Message Caption:
DeviceLock Security Subsystem
Content Verification Message Text:
Please wait while DeviceLock is verifying the "%CONTENT_NAME%" content.
Restore Defaults
OK Cancel

In the **Content verification message** dialog box, do the following:

USE THIS	TO DO THIS
Enable Content Verification Message	Enable or disable the display of the Content verification message.
	Select the <b>Enable Content Verification Message</b> check box to enable the display of the message.
	Clear the <b>Enable Content Verification Message</b> check box to disable the display of the message.
Content	Specify the text to display in the title bar of the message box.
Verification Message Caption	By default, the Content Verification Message Caption text is as follows:
	DeviceLock Security Subsystem
USE THIS	TO DO THIS
---	--
Content Verification Message Text	Specify the text to display in the message box. By default, the Content Verification Message Text is as follows:
<b>J</b>	Please wait while DeviceLock is verifying the %CONTENT_NAME% content.
	where <b>%CONTENT_NAME%</b> is the name of the file or protocol to be inserted. The file name is inserted when DeviceLock checks the content of files copied to a device. The protocol name is inserted when DeviceLock checks the content of data transmitted over the network.
<b>Restore Defaults</b>	Restore the default settings.

For a detailed description of the Content-Aware Rules feature, see "<u>Content-Aware</u> <u>Rules for Devices (Regular Profile)</u>" and "<u>Content-Aware Rules for Protocols (Regular</u> <u>Profile)</u>."

# **DeviceLock Enterprise Server(s)**

If you want to allow DeviceLock Service to send its logs to DeviceLock Enterprise Server, specify the name or IP address of this server's computer.

👼 DeviceLock Enterprise Server(s)	X
Computer Name: xpvirt	
DeviceLock Enterprise Server(s):	
xpvirt;vm2000server	Remove
OK	Cancel

Using the semicolon (;) as a separator you can specify several DeviceLock Enterprise Servers to uniformly spread the network load. At its startup, DeviceLock Service chooses one server for sending logs. If the selected server is unavailable, DeviceLock Service tries to choose another one from the list.

Make sure that DeviceLock Enterprise Server is properly installed and accessible for DeviceLock Service, otherwise logs will not be stored in the centralized database. For more information on how to install DeviceLock Enterprise Server, please read the <u>Installing DeviceLock Enterprise Server</u> section of this manual.

# Log Policy changes and Start/Stop events

You can enable the logging of changes in the DeviceLock Service's configuration and report the time when DeviceLock Service starts and stops. It is possible to log changes in permissions, audit rules, white lists and in other settings.

To allow this logging, enable the **Log Policy changes and Start/Stop events** parameter.

# DeviceLock Certificate

Use this parameter to install or remove a DeviceLock Certificate.

🖥 DeviceLock Certificate 🛛 💽 🔀
Computer Name: Local Computer Certificate Name:
DeviceLock Certificate [05/11/2006 01:28:52 PM]
Remove
OK Cancel

Specify the path to the public key in the **Certificate Name** parameter if you want to install the certificate. You can use the ... button to select the file with a public key.

To remove the public key, use the **Remove** button.

For more information about DeviceLock Certificates, please read the <u>DeviceLock</u> <u>Certificates</u> section of this manual.

# **Use Group Policy**

If DeviceLock Service is configured to work with Group Policy in an Active Directory domain, you can control the effective policy mode (Group Policy or Local Policy).

To activate the Group Policy mode for this DeviceLock Service, enable the **Use Group Policy** parameter. In this mode, all settings that you set via DeviceLock Management Console and DeviceLock Enterprise Manager are replaced by Group Policy settings.

To activate the Local Policy mode for this DeviceLock Service, disable the **Use Group Policy** parameter. In this mode, all settings that you set via DeviceLock Management Console and DeviceLock Enterprise Manager have a priority over Group Policy settings and replace them.

If DeviceLock Service was not configured to work with Group Policy, the **Use Group Policy** parameter is disabled and unavailable for changing.

If the **Use Group Policy** parameter is enabled but unavailable for changing, it means that the Group Policy mode always has a priority (the **Override Local Policy parameter** was enabled in DeviceLock Group Policy Manager) and the Local Policy

mode can't be enabled for this DeviceLock Service. For more information, please read the <u>Using DeviceLock Group Policy Manager</u> section of this manual.

## Fast servers first

DeviceLock Service can choose the fastest available DeviceLock Enterprise Server from the list of servers.

When this parameter is enabled, all servers specified in the **DeviceLock Enterprise Server(s)** parameter are divided into three groups depending on their network speed and preference is given to the fastest. If all of the fastest servers are unavailable, DeviceLock Service attempts to select a server from the group of next fastest servers and so on.

If the **Fast servers first** parameter is disabled, DeviceLock Service randomly selects a server from the list.

This parameter has an effect only if there is more than one server specified in the **DeviceLock Enterprise Server(s)** parameter.

# **Traffic priority**

DeviceLock supports traffic shaping, allowing you to define bandwidth limits for sending audit and shadow logs from DeviceLock Service to DeviceLock Enterprise Server.

📕 Traffic Priority	? 🛽
Computer Name: xpvirt	
OHigh	
Medium	
OLow	

You can set three types of traffic priority: high, medium and low.

When **High** is selected it means that 100% of bandwidth can be used. To allow use of only up to 50% of bandwidth, select **Medium**. Select **Low** to allow use of just up to 10% of bandwidth.

Please note that medium and low priorities have an effect only if the Quality of Service Packet Scheduler (QoS Packet Scheduler) component is installed on a computer running DeviceLock Service. Otherwise, the **Traffic priority** parameter is disabled and 100% of bandwidth is used. For more information on QoS, please refer to Microsoft's on-line article:

### Always show tray icon

Use this option to enable or disable the display of the DeviceLock Tray Notification Utility icon in the notification area of the taskbar on client computers. End users working on client computers can refresh the connection state (online or offline) of DeviceLock Service. To do so, they need to right-click the DeviceLock Tray Notification Utility icon area in the notification area of the taskbar, and then click **Refresh Current State**. End users can also click the DeviceLock Tray Notification Utility icon to view the latest DeviceLock message balloon shown for the notification in the notification area of a client computer.

To enable or disable the display of the DeviceLock Tray Notification Utility icon, rightclick **Always show tray icon** and then click **Enable/Disable**, or double-click **Always show tray icon**.

## Archives content inspection on read

Use this option to enable or disable content inspection of files within archives when users try to read archive files. For more information, see the description of the <u>Inspection of files within archives</u> feature. To enable or disable content inspection of files within archives, right-click **Archives content inspection on read** and then click **Enable/Disable**, or double-click **Archives content inspection on read**.

**Note:** If this option is disabled, inspection of images embedded in PDF files, RTF and Microsoft Office documents is also not performed.

# Archives content inspection on write

Use this option to enable or disable content inspection of files within archives when users try to write archive files. For more information, see the description of the <u>Inspection of files within archives</u> feature. To enable or disable content inspection of files within archives, right-click **Archives content inspection on write** and then click **Enable/Disable**, or double-click **Archives content inspection on write**.

**Note:** If this option is disabled, inspection of images embedded in PDF files, RTF and Microsoft Office documents is also not performed.

# Offline mode detection

Use this option to configure offline mode detection settings. You can define the network characteristics that DeviceLock uses to detect its connection state (whether it is online or offline). By default, DeviceLock works in offline mode when the network cable is not connected to the client computer.

To configure offline mode detection settings, right-click **Offline mode detection** and then click **Properties**, or double-click **Offline mode detection**.

×
]

You can choose any of the following options:

OPTION	DESCRIPTION
Server connectivity	Indicates that the connection state of a client computer is determined by whether or not it can connect to the specified DeviceLock Enterprise Server.
	Thus, a client computer works in online mode, if it can connect to any of the specified DeviceLock Enterprise Servers and send them audit and shadow logs. A client computer works in offline mode if it cannot authenticate with any of the specified DeviceLock Enterprise Servers or all of the specified DeviceLock Enterprise Servers become unavailable at the same time.
	<b>Best Practice:</b> The most reliable way to secure client/server communication is to use DeviceLock Certificate authentication. For client/server certificate authentication, the public key must be installed on client computers, while the private key must be installed on DeviceLock Enterprise Server(s).
	If the certificate (the private key) is installed only on DeviceLock Enterprise Server, the server will reject connections and client computers will work in offline mode. If the certificate (the public key) is installed only on client computers, the server and the client will authenticate each other once a connection is established though this type of authentication is less secure than certificate-based authentication. For detailed information on DeviceLock Certificates, see "DeviceLock Certificates."
Domain connectivity	Indicates that the connection state of a client computer is determined by whether or not it can connect to the appropriate Active Directory domain controller (a domain controller of the domain to which the client computer belongs).
	Thus, a client computer works in online mode, if it can connect to the appropriate domain controller. A client computer works in offline mode, if the appropriate domain controller becomes unavailable.
	A client computer that is not joined to a domain (a workgroup or stand-

OPTION	DESCRIPTION
	alone computer) always works in offline mode.
Wired connectivity	Indicates that the connection state of a client computer is determined by whether or not the network cable is connected to the Network Interface Card (NIC). This is the simplest and least secure method of detecting the connection state.
	Thus, a client computer works in online mode, if the network cable is connected to the NIC. A client computer works in offline mode, if the network cable is disconnected from the NIC. Please note that wireless network connections (Wi-Fi, etc.) and modem connections are ignored.
	This option is selected by default.

For detailed information on DeviceLock offline policies, see "<u>DeviceLock Security</u> <u>Policies (Offline Profile)</u>."

#### **DeviceLock Administrators**

This parameter allows you to define the list of user accounts with administrative access rights to DeviceLock Service.

🛃 DeviceLock Management		
File Help ← → € 🗷 📴 😰		
Smartline DeviceLock  Service Options  Service Options  Shadowing  Shadow Log Viewer  Shadow Log Viewer  DeviceLock Enterprise Server	View Export List Help	Access Full access Read-only Full access
Enables you to define Devicelock Adminis	strators	

Use the context menu available by a right mouse click on the **DeviceLock Administrators** item to open the configuration dialog box.

Computer Name: Local Comp	outer	
Enable Default Security		
Users		- 10
Add Delete	v	
Add Pelete NOTE: We strongly rec have local administrator connection to DeviceLo	ommend that account r privileges to ensure ck Service.	ts in this list proper
Add Delete NOTE: We strongly rec have local administrato connection to DeviceLo Enable Unhook Protection	ommend that account r privileges to ensure ck Service.	ts in this list proper

DeviceLock's default security configuration is based on Windows Access Control Lists (ACL). A user without administrative privileges can't connect to DeviceLock Service, modify its settings or remove it. Everything is controlled by the Windows security subsystem.

To turn on the default security based on Windows ACL, select the **Enable Default Security** check box.

**Note:** As described in the <u>Recommended Basic Security Measures</u> section of this manual, giving administrative privileges to regular users is strongly discouraged.

Users with local administrator privileges (i.e. members of the local Administrators group) can connect to DeviceLock Service using a management console and change permissions, auditing and other parameters. Moreover, such users can uninstall DeviceLock from their computers, disable or delete DeviceLock Service, modify a service's registry keys, delete a service's executable file, and so on. In other words, users with local administrator privileges can circumvent the default security based on Windows ACL.

However, if for some reason, users in your network have administrator privileges on their local computers, DeviceLock does provide another level of protection – DeviceLock Security. When DeviceLock Security is enabled, no one except authorized users can connect to DeviceLock Service or stop and uninstall it. Even members of the local Administrators group (if they are not on the list of authorized DeviceLock administrators) can't circumvent DeviceLock Security.

To turn on DeviceLock Security, clear the **Enable Default Security** check box.

Then you need to specify authorized accounts (users and/or groups) that can administer DeviceLock Service. To add a new user or user group to the list of accounts, click the **Add** button. You can add several accounts simultaneously.

To delete a record from the list of accounts, use the **Delete** button. Using Ctrl and/or Shift you can highlight and remove several records simultaneously.

To define which DeviceLock administrative actions are to be allowed for a user or user group, set the appropriate rights:

- Full access to enable full access to DeviceLock Service. Users can modify
  permissions, auditing and other parameters, remove and update DeviceLock
  Service.
- Change to enable change access to DeviceLock Service. Users can change settings, install, and uninstall DeviceLock Service, but they cannot add new users to the list of authorized accounts that can administer DeviceLock Service or change access rights for existing users in this list.
- **Read-only** to enable only the reading of permissions, auditing and other parameters. Users can run reports, view defined parameters but cannot modify anything or remove/update DeviceLock Service.

**Note:** We strongly recommend that accounts included in this list have local administrator privileges because, in some instances, installing, updating and uninstalling DeviceLock Service may require access rights to Windows Service Control Manager (SCM) and shared network resources.

Here is just one example of how to properly define a DeviceLock Administrators list: add a Domain Admins group with **Full access** rights. Because Domain Admins is a member of the local group Administrators on every computer in the domain, all members of Domain Admins will have full access to DeviceLock Service on every computer. However, other members of the local group Administrators will not be able to administer DeviceLock Service or disable it.

Also, by selecting the **Enable Unhook Protection** check box, you can turn on optional protection against anti-rootkit techniques that could be used to intentionally disable DeviceLock Service. When this protection is turned on, the DeviceLock Driver controls the integrity of its code. If a violation is found, DeviceLock causes Windows to stop with a fatal error (BSOD).

**Note:** Some antivirus, firewall and other low-level third-party software may conflict with the unhook protection and cause fatal errors (BSOD). We recommend that you enable this protection only for the systems where it was tested before.

## Auditing & Shadowing

These parameters allow you to tune up auditing and shadowing for DeviceLock Service.



Use the context menu available via a right mouse click on every parameter.

#### Local storage directory

Use this parameter to define where on the local disk cached data (for shadowing and content analysis) is stored.

崎 Local storage directory	
Computer Name: xpvirt	
Local Storage Directory	
%SystemRoot%\SHADOW	Default
ОК	Cancel

By default, DeviceLock Service uses the **%SystemRoot%\SHADOW** directory to store cached data (for shadowing and content analysis) on the local computer. %SystemRoot% is a standard environment variable that expands to a path to the Windows root folder (for example, C:\Windows). You can specify any other directory on any locally accessible hard disk.

DeviceLock Service protects this directory so regular users cannot access files inside it.

Make sure that there is enough space to store the data (if the user copies 1GB to the flash drive, then you need approximately 2GB available in local storage).

## Enable local storage quota

Enable this parameter to allow automatic cleanup of the locally stored cached data (for shadowing and content analysis).

When this parameter is enabled you can also configure **Cleanup files older than** (days) and Local storage quota (%) parameters (see below).

## Cleanup files older than (days)

You can define the number of days that should pass before cached data (for shadowing and content analysis) can be automatically deleted from the local storage.

😰 Cleanup files older than (days)
Computer Name: xpvirt
Cleanup Files Older Than 30 📩 days
OK Cancel

Select the **Cleanup Files Older Than** check box and type or select the number of days to allow automatic cleanup.

# Local storage quota (%)

You can define a disk quota for cached data (for shadowing and content analysis).

🖀 Local storage quota (%)	×
Computer Name: xpvirt	
Local Storage Quota 60 🕂 %	
	_
OK Cancel	

Specify the maximum percentage (from 5 to 100) of free disk space that can be used by cached data in the **Local Storage Quota** parameter.

If the quota is not used (i.e. the **Enable local storage quota** parameter is disabled) then DeviceLock Service uses all available space on the disk where the directory specified in the **Local storage directory** parameter is located.

When the total size of the directory specified in the **Local storage directory** parameter reaches the quota, DeviceLock Service either starts deleting old data (if the **Cleanup files older than (days)** parameter is enabled) or stops data shadowing and content analysis (if the **Cleanup files older than (days)** parameter is disabled or there is nothing to delete).

## Shadow zero-length files

Enable this parameter to allow shadowing of files whose size is zero.

Even if the file contains no data at all, it is still possible to transfer some information in its name and path (up to several kilobytes) that is why you may need to enable shadowing for zero-length files.

#### Prevent data transfer on errors

By enabling this parameter, you can prevent users from writing data when shadowing or content analysis is not possible.

You can be sure that users can transfer information only when shadowing and Content-Aware Rules are working normally (e.g. there is enough local disk space to store cached data).

When the **Prevent data transfer on errors** parameter is enabled, the total size of the directory specified in the **Local storage directory** parameter reaches the quota specified in **Local storage quota (%)** and there is no data that can be deleted, DeviceLock Service stops shadowing and content analysis and blocks any user attempt to copy the data.

#### Audit log type

Using this parameter you can define what log should be used to store audit records.



There are three options to choose:

- **Event Log** only the standard local Windows Event Log is used to store audit records.
- **DeviceLock Log** only the protected proprietary log is used to store audit records. The data from this log is sent to DeviceLock Enterprise Server and is stored centrally in the database.
- Event & DeviceLock Logs both logs are used to store audit records.

## Audit Log Settings

Use **Audit Log Settings** to specify the maximum size of the audit log and overwrite options.

Audit Log Settings 🛛 💽 🗙
Log size
Maximum log size: 512 🛟 KB
When maximum log size is reached:
O Qverwrite events as needed
Overwrite events older than 7 ♀ days
O Do not overwrite events (clear log manually)
OK Cancel

For a detailed description of the audit log settings, see "<u>Audit Log Settings</u> (<u>Service</u>)."

#### Transfer shadow data to server

Use this parameter to enable or disable the moving of all shadow data to DeviceLock Enterprise Server. If **Transfer shadow data to server** is disabled, only audit data from the DeviceLock proprietary log (if this log is used) is sent to DeviceLock Enterprise Server, while all shadow data is stored locally and is not transferred to the server.

# Anti-keylogger

These parameters allow you to tune up DeviceLock's ability to detect hardware keyloggers and to define what DeviceLock Service should do when a keylogger is found.

Hardware keyloggers are devices that record keystrokes. DeviceLock Service can detect USB keyloggers and block keyboards connected to them. Also, DeviceLock Service can block PS/2 keyloggers.



Use the context menu available via a right mouse click on every parameter.

## **Block keyboard**

Enable this parameter to block the keyboard connected to the hardware USB keylogger when it is detected.

Since DeviceLock Service starts before the user logs in to Windows, it can block the keyboard and prevent the user from typing the password.

**Note:** Some hardware keyloggers continue to record keystrokes even if the keyboard is blocked and not functioning in Windows. This happens because such keyloggers are standalone devices and do not require any OS or drivers.

#### Log event

You can instruct DeviceLock Service to write an event to the audit log when the hardware USB keylogger is detected.

#### Treat any USB hub as keylogger

By enabling this parameter, you can instruct DeviceLock Service to treat any external USB hub to which the keyboard is connected as a hardware keylogger.

Otherwise, DeviceLock Service detects only those hub keyloggers that exist in its internal database.

## Notify user

You can define a custom message to be displayed to users when DeviceLock Service detects hardware USB keyloggers.

Since DeviceLock Service starts before the user logs in to Windows, this message can alert the user and prevent him/her from typing the password on the keyboard connected to the USB keylogger.

🚯 Notify User 🔹 💽 🔀
Computer Name: xpvirt
✓ Notify User
Notification Caption
DeviceLock Security Subsystem
Notification Text
The hardware keylogger is detected on "%DEVICE%"! Please check how your keyboard is connected to the USB port.
Restore Defaults
OK Cancel

To enable this custom message, select the **Notify User** check box.

Also, you can define additional parameters, such as:

- Notification Caption the text to be displayed as a caption. You can use the predefined macros within the text: %DEVICE% – inserts the name of the keyboard's device (for example, USB Keyboard) received from the system.
- **Notification Text** the main text of the message. You can use the predefined macros described above within the text.

# PS/2 keyboard scrambling

By enabling this parameter, you can prevent PS/2 keyloggers from recording keystrokes. DeviceLock Service is unable to detect PS/2 keyloggers and notify users about their presence but it obfuscates PS/2 keyboard's input and forces PS/2 keyloggers (if any) to record some garbage instead of the real keystrokes.

**Note:** When PS/2 keyboard scrambling is enabled while working with the PS/2 KVM switch, the switching between computers will not work from the keyboard.

# Encryption

DeviceLock Service can detect disks (USB flash drives and other removable media) encrypted by third-party products and apply special "encrypted" permissions to them.

This feature allows you to define more flexible access control policies and helps to prevent writing sensitive data to unencrypted media.



Currently DeviceLock supports these third-party products for encrypting data on removable storage devices:

- DriveCrypt DeviceLock Service can detect DriveCrypt's encrypted removable storage devices and apply special "encrypted" permissions to them when the DriveCrypt product is installed on the computer where DeviceLock Service is running and Integration is enabled. For more information on DriveCrypt, please visit: <u>http://www.securstar.com</u>
- Lexar JD SAFE S3000 and Lexar JD SAFE S3000 FIPS DeviceLock Service can detect Lexar<sup>™</sup> JumpDrive SAFE S3000 USB flash drives (FIPS-

certified and/or regular) and apply special "encrypted" permissions to them in the event that a user plugs such a device into a computer where DeviceLock Service is running and **Integration** is enabled. For more information on Lexar<sup>™</sup> JumpDrive SAFE S3000, please visit Lexar's Web site: <u>http://www.lexar.com/products/enterprise-usb-solutions</u>.

- Lexar SAFE PSD DeviceLock Service can detect Lexar<sup>™</sup> SAFE PSD S1100 USB flash drives and apply special "encrypted" permissions to them in the event that a user plugs such a device into a computer where DeviceLock Service is running and Integration is enabled. For more information on Lexar<sup>™</sup> SAFE PSD S1100, please visit Lexar's Web site: http://www.lexar.com/about/newsroom/press-releases/lexar-begins-shippingits-award-winning-safe-psd-s1100-secure-enterpri.
- PGP Whole Disk Encryption DeviceLock Service can detect PGPencrypted removable storage devices and apply special "encrypted" permissions to them when the PGP® Whole Disk Encryption product is installed on the computer where DeviceLock Service is running and Integration is enabled. For step-by-step instructions on how to install and use PGP® Whole Disk Encryption with DeviceLock, please refer to the PGP/DeviceLock Integration Guide created by PGP. For more information on PGP® Whole Disk Encryption, please visit PGP's Web site: http://www.pgp.com/products/wholediskencryption/index.html.
- SafeDisk DeviceLock Service can detect encrypted SafeDisk containers (stored on USB flash drives and other removable media) and apply special "encrypted" permissions to them if **Integration** is enabled. Using these "encrypted" permissions you can, for example, allow writing only to encrypted removable devices and deny writing to unencrypted media. For more information on ViPNet Safe Disk, visit the following Web site <u>http://www.infotecs.biz/Soft/safe\_disk.htm</u>.

**Note:** To get access to SafeDisk containers and work with their contents, users should have at least read access to unencrypted Removable devices.

- SafeGuard DeviceLock Service can detect Sophos SafeGuard Easyencrypted disks (USB flash drives and other removable media) and apply special "encrypted" permissions to them if **Integration** is enabled. Using these "encrypted" permissions you can, for example, allow writing only to encrypted removable devices and deny writing to unencrypted media. For more information on SafeGuard Easy, visit the <u>Sophos Web site</u>.
- TrueCrypt DeviceLock Service can detect TrueCrypt's encrypted removable storage devices and apply special "encrypted" permissions to them when the TrueCrypt product is installed on the computer where DeviceLock Service is running and Integration is enabled. For more information on TrueCrypt, please visit TrueCrypt's Web site: <u>http://www.truecrypt.org/</u>.

**Note:** If the TrueCrypt's volume type is "**File-hosted (container)**", then to get access to this container and work with its content, the user should have at least read access to unencrypted Removable devices.

 Windows BitLocker To Go - DeviceLock Service can detect BitLocker To Goencrypted drives and apply special "encrypted" permissions to them if Integration is enabled. For more information on the BitLocker Drive Encryption feature of Windows 7, refer to the <u>Microsoft documentation</u>.

Note: If integration with Windows BitLocker To Go is enabled, the Deny write access to removable drives not protected by BitLocker policy setting (located in Computer Configuration\Administrative Templates\Windows Components\BitLocker Drive Encryption\Removable Data Drives) cannot be enabled.

If you do not want to allow DeviceLock Service to detect one of the encryption products listed above and to apply special "encrypted" permissions to storage devices encrypted by it, disable **Integration** under the product's section in the management console.

For more information on "encrypted" permissions, please read the <u>Permissions</u> section of this manual.

**Note:** DeviceLock does not ship with third-party encryption products and does not require them for its own functioning. The integrated functioning of DeviceLock and a third-party encryption product will only work when the third-party product is properly installed, configured and running on the same computer where DeviceLock Service is running.

# Devices

Configuration parameters available under this item allow you to access main functions of DeviceLock – permissions, auditing, shadowing, white lists and so on.



Use the context menu available with a right mouse click on the Devices item to access the **Display Available Devices Only** flag. If it is checked, DeviceLock Management Console shows only those device types currently available on the current computer. Otherwise, you will see every type of device that DeviceLock

supports. This is useful when you want to set permissions to device types that are not yet installed or are currently unplugged from the computer.

# Permissions (Regular Profile)

There is a list of device types for which you can define user-level permissions.

e Action View Help			
-			
DeviceLock	Name /	Regular	Offline
DeviceLock Service (Local, WINDPPROSP3)	BlackBerry	Full Access	Not Configured
Service Options	8 Bluetooth	Full Access	Not Configured
Devices	Clipboard	Full Access	Not Configured
E Permissions	DVD/CD-ROM	Full Access	Not Configured
66" Audong & Shadowing	FireWire port	Full Access	Not Configured
Mada White List	Floppy	Full Access	Not Configured
Dh Content-Aware Dides	Hard disk	Full Access	Not Configured
Security Settings	A Infrared port	Full Access	Not Configured
Protocols	Phone Phone	Full Access	Not Configured
Audit Log Viewer	Palm	Full Access	Not Configured
Bhadow Log Viewer	Parallel port	Full Access	Not Configured
Cocal, WIND	Prinker	Full Access	Not Configured
DeviceLock Content Security Server	Removable	Full Access	Not Configured
	F Serial port	Full Access	Not Configured
	Tape	Full Access	Not Configured
	USB port	Full Access	Not Configured
	TWF	Full Access	Not Configured
N	Windows Mobile	Full Access	Not Configured

**Note:** When you set permissions for a device type, you set these permissions for every device belonging to that type. It is impossible to set different permissions for two different devices if they are of the same type (for example, both are removable drives). To define different permissions for USB devices even if they are of the same type, use the <u>White List</u> function.

There are two levels of control: the interface (port) level and the type level. Some devices are checked at both levels, while others only at the one level – either interface (port) or type.

For more information on how access control works, please read the <u>Managed Access</u> <u>Control</u> section of this manual.

DeviceLock supports the following types of devices:

- **BlackBerry** (type level) includes all BlackBerry devices with any type of the connection interface (USB, Bluetooth) to the computer.
- **Bluetooth** (type level) includes all internal and external Bluetooth devices with any type of the connection interface (USB, PCMCIA, etc.) to the computer.
- **Clipboard** includes the Windows Clipboard. DeviceLock controls paste operations for data placed on the clipboard.

- **DVD/CD-ROM** (type level) includes all internal and external CD/DVD devices (readers and writers) with any connection interface (IDE, SATA, USB, FireWire, PCMCIA, etc).
- **FireWire port** (interface level) includes all devices that can be plugged into the FireWire (IEEE 1394) port, except the hub devices.
- **Floppy** (type level) includes all internal and external floppy drives with any connection interface (IDE, USB, PCMCIA, etc.). It is possible that some nonstandard floppy drives are recognized by Windows as removable devices, in this case DeviceLock treats such floppy drives as the **Removable** type as well.
- Hard disk (type level) includes all internal hard drives with any connection interface (IDE, SATA, SCSI, etc). DeviceLock treats all external USB, FireWire and PCMCIA hard drives as the **Removable** type. Also, DeviceLock treats as **Removable** some internal hard drives (usually SATA and SCSI) if they support the hot plug feature and Windows is not installed and running on them.

**Note:** Even if you deny access to the Hard disk type, users with local administrative privileges (the SYSTEM user and members of the local Administrators group) still can access the partition where Windows is installed and running.

- **Infrared port** (interface level) includes all devices that can be connected to the computer via the infrared (IrDA) port.
- **iPhone** (type level) includes all iPhone, iPod Touch, and iPad devices. DeviceLock controls iPhone, iPod Touch, and iPad devices that are working with a PC through the iTunes application or its API.
- **Palm** (type level) includes all Palm OS devices with any type of connection interface (USB, COM, IrDA, Bluetooth, WiFi) to the computer. DeviceLock controls Palm OS devices that are working with a PC through the HotSync application.
- **Parallel port** (interface level) includes all devices that can be connected to the computer via the parallel (LPT) ports.
- Printer (type level) includes all local and network printers with any type of connection interface (USB, LPT, Bluetooth, etc) to the computer. DeviceLock can even optionally control virtual printers which do not send documents to real devices, but instead print to files (for example, PDF converters).
- Removable (type level) includes all internal and external devices with any connection interface (USB, FireWire, PCMCIA, IDE, SATA, SCSI, etc) that are recognized by Windows as removable devices (for example, USB flash drives, ZIP drives, card readers, magneto-optical drives, and so on). DeviceLock treats all external USB, FireWire and PCMCIA hard drives as the Removable type as well. Also, DeviceLock treats as Removable some internal hard drives (usually SATA and SCSI) if they support the hot plug feature and Windows is not installed and running on them.

- **Serial port** (interface level) includes all devices that can be connected to the computer via the serial (COM) ports, including internal modems.
- **Tape** (type level) includes all internal and external tape drives with any connection interface (SCSI, USB, IDE, etc).
- **USB port** (interface level) includes all devices that can be plugged into the USB port, except the hub devices.
- **WiFi** (type level) includes all internal and external WiFi devices with any type of connection interface (USB, PCMCIA, etc.) to the computer.

**Note:** Using the WiFi type you can control user access to the hardware device but not to the network.

• Windows Mobile (type level) – includes all Windows Mobile devices with any type of connection interface (USB, COM, IrDA, Bluetooth, WiFi) to the computer. DeviceLock controls Windows Mobile devices that are working with a PC through the Windows Mobile Device Center (WMDC) or Microsoft ActiveSync application or its API.

**Note:** You can define different online vs. offline permissions for the same user or sets of users. Online permissions (Regular Profile) apply to client computers that are working online. Offline permissions (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to set offline permissions, see "Managing Offline Permissions."

To set online (regular) permissions for a device type, highlight it (use Ctrl and/or Shift to select several types simultaneously) and select **Set Permissions** from the context menu available by a right mouse click. Alternatively, you can press the appropriate button on the toolbar.

Permissions Devices Type(s): USB port														? 2
Computer Name: Local Comput Users	er	(f 12	• 2	• •	• •	8	• 10	• 12	• 2	• •	• 6	• 8	• 10	£ 12
SYSTEM		All		1					Π					
		Sunday												
Add	Delete Set Default	Monday						Π				Π	Π	
User's Rights	Allow	Tuesday												
<ul> <li>Generic Read</li> </ul>		Wednesday										Ш		
Write Format		Thursday										Ш	Ш	
Eject		Friday												
		Saturday												
				Mon	day t I - Alk	hrough wed T	ime 🗆	- Denie	12 To ed Tim	e 12				
		Security Setting	10	USB	White	List	]							
								OK		ci	ncel		Ap	pły –

The names of the users and user groups assigned to a device type are shown in the list of accounts on the top left-hand side of the **Permissions** dialog box.

To add a new user or user group to the list of accounts, click **Add**. You can add several accounts simultaneously.

Select Users or Groups	? 🛛
Select this object type:	
Users or Groups	Dbject Types
From this location:	
vm2000ad.com	Locations
Enter the object names to select (examples):	
Administrator; Guest	Check Names
Advanced	OK Cancel

To delete a record from the list of accounts, use the **Delete** button. Using CTRL and/or SHIFT you can select and remove several records simultaneously.

ACCOUNT/ DEVICE TYPE	EVERYONE	ADMINISTRATORS	SYSTEM
BlackBerry	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
Bluetooth	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
Clipboard	Generic: Copy to	Generic: Copy to	Generic: Copy to
	clipboard	clipboard	clipboard
	Special Permissions:	Special Permissions:	Special Permissions:
	Copy Text, Copy	Copy Text, Copy	Copy Text, Copy
	Image, Copy Audio,	Image, Copy Audio,	Image, Copy Audio,
	Copy File,	Copy File, Screenshot,	Copy File,
	Screenshot, Copy	Copy Unidentified	Screenshot, Copy
	Unidentified Content	Content	Unidentified Content
DVD/CD-ROM	Generic: Read, Write,	Generic: Read, Write,	Generic: Read,
	Eject	Eject	Write, Eject
FireWire port	Generic: Read, Write,	Generic: Read, Write,	Generic: Read,
	Eject	Format, Eject	Write, Format, Eject
Floppy	Generic: Read, Write,	Generic: Read, Write,	Generic: Read,
	Eject	Format, Eject	Write, Format, Eject
Hard disk	Generic: Read, Write	Generic: Read, Write,	Generic: Read,

Use the **Set Default** button to set default permissions for devices. Default permissions are enabled by using the following access selections:

#### DeviceLock Management Console

ACCOUNT/ DEVICE TYPE	EVERYONE	ADMINISTRATORS	SYSTEM
		Format	Write, Format
Infrared port	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
iPhone	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
Palm	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
Parallel port	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
Printer	Generic: Print	Generic: Print	Generic: Print
Removable	Generic: Read, Write, Eject	Generic: Read, Write, Format, Eject	Generic: Read, Write, Format, Eject
	Encrypted: Read, Write, Format	Encrypted: Read, Write, Format	Encrypted: Read, Write, Format
Serial port	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
Таре	Generic: Read, Write, Eject	Generic: Read, Write, Format, Eject	Generic: Read, Write, Format, Eject
USB port	Generic: Read, Write, Eject	Generic: Read, Write, Format, Eject	Generic: Read, Write, Format, Eject
WiFi	Generic: Read, Write	Generic: Read, Write	Generic: Read, Write
Windows Mobile	Generic: Read, Write, Execute	Generic: Read, Write, Execute	Generic: Read, Write, Execute

Using special time control, you can define a time when the selected user or user group will or will not have access to devices. Time control appears at the top-right side of the **Permissions** dialog box. Use the left mouse button and select the allowed time. To select a denied time use the right mouse button. Also, you can use the keyboard to set times – arrow keys for navigation and the spacebar to toggle allowed/denied time.

To define which actions on devices are to be allowed for a user or user group, set the appropriate rights. All rights are divided into three groups: **Generic**, **Encrypted**, and **Special Permissions**. Each group has its own set of rights:

- **Generic** Generic rights do not apply to devices that are recognized by DeviceLock Service as encrypted devices. For more information on encryption integration, please read the <u>Encryption</u> section of this manual.
  - **Read** to enable data reading from the device. Applies to all device types except Clipboard and Printer.
  - Write to enable data writing to the device. With the exception of Windows Mobile, this right can be enabled for all devices only if Read is selected in the Generic group. It cannot be disabled for BlackBerry,

Bluetooth, Infrared port, Parallel port, Serial port and WiFi device types. When **Write** is disabled for USB and FireWire ports it has the following effects: storage devices such as flash drives, floppies, hard disks, DVD/CD-ROMs, etc. can be read, but not written to; non-storage devices such as printers, scanners, etc. cannot be accessed.

- Format to enable the formatting, checking, and any other direct access of drives. You can enable this right only if **Read** is selected in the **Generic** group. Applies only to FireWire port, Floppy, Hard disk, Removable and USB port device types. When this right is enabled for USB and FireWire ports it affects only storage devices plugged into these ports.
- Eject to enable ejection of the media. You can enable this right only if Read is selected in the Generic group. This right controls only ejection via software. Hardware ejection using the eject button on a device's front panel cannot be prevented. Applies only to DVD/CDROM, FireWire port, Floppy, Removable and USB port device types. When this right is enabled for USB and FireWire ports it affects only storage devices plugged into these ports.
- **Execute** to enable the remote code execution on the device's side. Applies only to the Windows Mobile device type.
- **Print** to enable document printing. Applies only to the Printer device type.
- **Copy to clipboard** to enable data pasting from the clipboard. Applies only to the Clipboard device type. This right automatically grants full access to the clipboard.
- **Encrypted** encrypted rights only apply to devices that are recognized by DeviceLock Service as encrypted devices. For more information on encryption integration, please read the <u>Encryption</u> section of this manual.
  - **Read** to enable data reading from an encrypted device. Applies only to the Removable device type.
  - Write to enable data writing to an encrypted device. You can enable this right only if **Read** is selected in the **Encrypted** group. Applies only to the Removable device type.
  - Format to enable the formatting, checking, and any other direct access of encrypted drives. You can enable this right only if **Read** is selected in the **Encrypted** group. Applies only to the Removable device type.
- Special Permissions these rights only apply to iPhone, Windows Mobile, Palm and Clipboard device types. The content types (*Calendar, Contacts, Tasks*, etc.) that are controlled by these rights for iPhone, Windows Mobile, and Palm devices represent the same content types that exist in iTunes, HotSync, Microsoft ActiveSync and WMDC applications. For Palm devices, you can enable any Write right only if the corresponding Read right is also enabled.
  - **Read Calendar** to enable reading the calendar on a mobile device from a PC.

- Write Calendar to enable writing to a calendar on a mobile device from a PC.
- Read Contact to enable reading contacts on a mobile device from a PC.
- Write Contact to enable writing contacts from a PC to a mobile device.
- **Read E-mail** to enable reading e-mails on a mobile device from a PC. For iPhone, this content type represents e-mail account settings but not messages because iTunes does not support sync of messages.
- Write E-mail to enable writing e-mails from a PC to a mobile device. For iPhone, this content type represents e-mail account settings but not messages because iTunes does not support sync of messages.
- Read Attachment to enable reading e-mail attachments on a Windows Mobile device from a PC. You can enable this right only if Read E-mail is selected in the Special Permissions group.
- Write Attachment to enable writing e-mail attachments from a PC to a Windows Mobile device. You can enable this right only if Write Email is selected in the Special Permissions group.
- **Read Favorite** to enable reading favorites on a Windows Mobile device and iPhone from a PC.
- Write Favorite to enable writing favorites from a PC to a Windows Mobile device and iPhone.
- **Read File** to enable reading files on a mobile device from a PC. For iPhone, data flows of the *Applications* iTune's type are treated as files.
- Write File to enable writing files from a PC to a mobile device. For a
  Palm device this right also enables Write Document in the Special
  Permissions group. For iPhone, data flows of the Applications iTune's
  type are treated as files.
- Read Media to enable reading media content using Windows Media Player on a Windows Mobile device and reading media files on a Palm device and iPhone from a PC. You can enable this right only if Read Files is selected in the Special Permissions group. For a Windows Mobile device, this option also requires selecting Execute from the Generic group. For iPhone, the media content type consists of the following iTunes types: *Ringtones, Music, Audiobooks, Photos, Podcasts* (Audio & Video), *Movies, TV shows, Rented Movies*.
- Write Media to enable writing media content using Windows Media Player to a Windows Mobile device and writing media files to a Palm device and iPhone from a PC. You can enable this right only if Write Files is selected in the Special Permissions group and, for a Windows Mobile device, if Execute is selected from the Generic group. For iPhone, the media content type consists of the following iTunes types: *Ringtones, Music, Audiobooks, Photos, Podcasts* (Audio & Video), *Movies, TV shows, Rented Movies*.
- Read Backup to enable creating the iPhone backup by reading the device data from a PC.

**Note:** An iPhone device is backed up by iTunes each time users sync with iTunes (automatically on the first sync, every time they connect it to the computer). To allow synchronization to complete successfully, grant the **Read Backup** permission to users

for the **iPhone** device type. Otherwise, if iTunes automatically creates an iPhone backup, the synchronization session will be interrupted.

To avoid interrupting the synchronization process, users should set iTunes to sync only the content to which they are allowed access.

- Write Backup to enable restoring iPhone by writing the device backup data from a PC.
- Read Note to enable reading notes on a mobile device from a PC.
   For a Palm device this right controls *Memos* and *Note Pad* content types.
- Write Note to enable writing notes from a PC to a mobile device.
   For a Palm device this right controls *Memos* and *Note Pad* content types.
- **Read Pocket Access** to enable reading Pocket Access databases on a Windows Mobile device from a PC.
- Write Pocket Access to enable writing Pocket Access databases from a PC to a Windows Mobile device.
- **Read Task** to enable reading tasks on a mobile device from a PC.
- Write Task to enable writing tasks from a PC to a mobile device.
- Read Expense to enable reading Palm Expense application data on a Palm device from a PC.
- Write Expense to enable writing Palm Expense application data from a PC to a Palm device.
- Read Document to enable reading Palm documents on a Palm device from a PC. You can enable this right only if Read Files is selected in the Special Permissions group.
- Write Document to enable writing Palm documents from a PC to a Palm device. You can enable this right only if Write Files is selected in the Special Permissions group.
- **Read Unidentified Content** to enable reading any other uncategorized content type on a Windows Mobile device from a PC.
- Write Unidentified Content to enable writing any other uncategorized content type from a PC to a Windows Mobile device.
- **Copy Text** to enable pasting text data from the clipboard.
- **Copy Image** to enable pasting graphical data from the clipboard.
- **Copy Audio** to enable pasting audio data from the clipboard.
- **Copy File** to enable pasting files from the clipboard.
- **Screenshot** to enable capturing screen shots of the entire screen, the active window or any segment of the screen to the clipboard.

**Note:** Because screen shots captured using screen capture tools and utilities are saved directly to files while screen shots captured by pressing the PRINT SCREEN key are first copied to the clipboard and then must be pasted into a separate program (for example, Microsoft Word or Paint), different access rights are required to control access to screen shots. To allow users to capture screen shots using screen capture tools and utilities, you must grant them only the Screenshot right. To allow users to capture screen shots by pressing the PRINT SCREEN key, you must grant them the Screenshot and Copy Image rights.

If users do not have the Screenshot right, they cannot capture screen shots using the PRINT SCREEN key or screen capture tools and utilities.

• **Copy Unidentified Content** - to enable pasting any other uncategorized content type from the clipboard.

**Note:** The Copy Text, Copy Image, Copy Audio, Copy File, and Copy Unidentified Content rights do not control data copying to the clipboard. Users can always copy data to the clipboard regardless of the rights they have.

**Note:** If the access (read and/or write) to some content type is denied during the iPhone or Windows Mobile synchronization process, you have to replug the device in order to continue using the iPhone or Windows Mobile device.

When users attempt to synchronize a Palm handheld device over a network and DeviceLock denies access to some content type, the synchronization session is interrupted. To avoid this situation, users should set the HotSync application to sync only the content to which they are allowed access before attempting synchronization.

If all rights are enabled for the user account it means that this account has "full access" rights to a device. If all rights are disabled for the user account it means that this account has "no access" rights to a device.

**Note:** The "no access" right has a priority over all other rights. It means that if the group to which some user belongs has the "no access" right but this user has "full access", the user still cannot access a device. If you want to deny access for some user or group, you can just remove it from the account's list, it is not necessary to add it with "no access".

Also, the Everyone user has a priority over all other accounts. It means that if Everyone has the "no access" right, no one can access a device.



Even if you deny access to hard disks, users with local administrative privileges (the SYSTEM user and members of the local Administrators group) still can access the partition where Windows is installed and running.

We recommend that you add only those accounts (users and/or groups) to the list which should be able to access a device. If the account's list is empty (contains no records at all) then no one can access a device.

Also, it is recommended to add the SYSTEM user with "full access" to hard disks and DVD/CD-ROMs.

On some systems, users may receive the following message when they log in.

Messenger Service	×
Message from VM2000PR0FSP4 to VM2000PR0FSP4 on 7/13/2	2006 1:57:33 PM
From: NtmsSvc on VM2000PR0FSP4	
User: Subj: **ADMINISTRATOR ALERT**	
Failed to configure a(n) CdRom drive device. Check event log for	details
ОК	

It means that the SYSTEM user cannot access DVD/CD-ROM. To avoid this message, set the "full access" right for SYSTEM on DVD/CD-ROM.

# Auditing & Shadowing (Regular Profile)

There is a list of device types for which you can define user-level audit and shadowing rules.

SeviceLock Management Console			
File Action View Help			
JeviceLock	Name /	Regular	Offline
DeviceLock Service (Local, WINXPPROSP3)	BlackBerry	No Audit	Not Configured
Service Options	Bluetooth	No Audit	Not Configured
E Devices	Clipboard	No Audit	Not Configured
C Permissions	DVD/CD-ROM	No Audit	Not Configured
B ISB Davisar White List	FireWire port	No Audit	Not Configured
Meda White List	Floppy	No Audit	Not Configured
Content-Aware Bules	Hard disk	No Audit	Not Configured
Scoulty Settings     Frotocols     Audt Log Viewer	A Infrared port	No Audit	Not Configured
	Phone	No Audit	Not Configured
	🚺 Palm	No Audit	Not Configured
- Bhadow Log Viewer	Parallel port	No Audit	Not Configured
DeviceLock Enterprise Server (Local, WIND)	I Printer	No Audit	Not Configured
DeviceLock Content Security Server	Removable	No Audit	Not Configured
	Serial port	No Audit	Not Configured
	Tape	No Audit	Not Configured
	CONT USB port	No Audit	Not Configured
	TWF	No Audit	Not Configured
< >	Windows Mobile	No Audit	Not Configured
Local Policy is enabled for this machine (Regular Profi	le).	Local Computer	

There is not much difference between setting up permissions and defining audit and shadowing rules so at fist read the <u>Permissions</u> section of this manual.

DeviceLock Service can use the standard Windows event logging subsystem to log a device's information. It is extremely useful for system administrators because they can use any event log reading software to view the DeviceLock audit log. You can use the standard Event Viewer, for example. Also, DeviceLock Service can use its own protected proprietary log. The data from this log is sent to DeviceLock Enterprise Server and stored centrally in the database. To define what log should be used, set the **Audit log type** parameter in <u>Service Options</u>.

DeviceLock Management Console has its own built-in audit log viewer that represents information from the event log in a more convenient form. For more information, see "Audit Log Viewer (Service)."

To view the audit log stored on DeviceLock Enterprise Server, use the <u>server's audit</u> log viewer.

Also there is an extended audit's feature called data shadowing – the ability to mirror all data copied to external storage devices or transferred through serial and parallel ports. A full copy of the data is logged. The shadow log is stored locally in the special directory (see "<u>Service Options</u>") and then can be transferred to the DeviceLock Enterprise Server specified in <u>Service Options</u> to store it in the SQL database.

To view the locally stored shadow log, use DeviceLock Management Console's built-in shadow log viewer. For more information, see "<u>Shadow Log Viewer (Service)</u>."

To view the shadow log stored on DeviceLock Enterprise Server, use the <u>server's</u> <u>shadow log viewer</u>.

**Note:** You can define different online vs. offline audit and shadowing rules for the same user or sets of users. Online audit and shadowing rules (Regular Profile) apply to client computers that are working online. Offline audit and shadowing rules (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "<u>DeviceLock Security Policies (Offline Profile</u>)." For information about how to define offline audit and shadowing rules, see "<u>Managing Offline Audit and Shadowing Rules</u>."

To define online (regular) audit and shadowing rules for a device type, highlight it (use Ctrl and/or Shift to select several types simultaneously) and select **Set Auditing & Shadowing** from the context menu available by the right mouse click. Alternatively, you can press the appropriate button on the toolbar.

6 Auditing & Shadowing		? 🛛
Devices Type(s): Windows Mobile Computer Name: Local Computer Audit Allowed Audit Denied		
Users REveryone	3 12 • 2 • 4 • 6 • 8 • 10 • 12 • 2 • 4 • 6 • 8 • 10	• 12
2 Users	Al	
	Sunday	
Add Delete Set Default	Monday	
User's Rights Allow	Tuesday	
🗟 Audit	Wednesday	
Read V Write V	Thursday	
Execute	Friday	
Write Non-files	Saturday	
Shadowing Write Write Non-files	Sunday through Saturday From 12 To 12  - Audit Time - Non-audit Time	
	OK Cancel /	Apply

There are two types of user access that can be logged to the audit log:

- **Allowed** all access attempts that were permitted by DeviceLock Service, that is, the user was able to access a device.
- **Denied** all access attempts that were blocked by DeviceLock Service, that is, the user was not able to access a device.

To enable logging to the audit log for one or both of these access types, check **Audit Allowed** and/or **Audit Denied**. These flags are not linked to users/groups, they are related to a whole device type.

The names of the users and user groups assigned to a device type are shown in the list of accounts on the top left-hand side of the **Auditing & Shadowing** dialog box.

To add a new user or user group to the list of accounts, click **Add**. You can add several accounts simultaneously.

To delete a record from the list of accounts, use the **Delete** button. Using CTRL and/or SHIFT you can select and remove several records simultaneously.

Use the **Set Default** button to set default audit and shadowing rules for devices: members of the Users group and the Everyone account have **Read** and **Write** audit rights and shadowing is disabled for them.

Using special time control, you can define a time when the audit rule for the selected user or user group will or will not be active. Time control appears at the top-right side of the **Auditing & Shadowing** dialog box. Use the left mouse button and select the time when the rule is active (audit time). To select a time when the rule is not active (non-audit time), use the right mouse button. Also, you can use the keyboard to set times – arrow keys for navigation and the spacebar to toggle audit/non-audit time.

To define which user's actions on devices are to be logged to either the audit or shadow log, set the appropriate audit rights. All rights are divided into two groups: **Audit** and **Shadowing**. Each group has its own set of rights:

- **Audit** rights that belong to this group are responsible for actions logged into the audit log.
  - **Read** to log the read access attempts. For BlackBerry, Bluetooth, FireWire port, Infrared port, Parallel port, Serial port, USB port and WiFi device types, you can enable this right only if **Write** is selected in the **Audit** group.
  - Write to log the write access attempts. For BlackBerry, Bluetooth, FireWire port, Infrared port, Parallel port, Serial port, USB port and WiFi device types, you can enable this right only if **Read** is selected in the **Audit** group.

- **Print** to log all attempts to send documents to printers. Applies only to the Printer device type.
- **Execute** to log access attempts to remotely execute a code on the device's side. Applies only to the Windows Mobile device type.
- Read Non-files to log the read access attempts for non-file objects (*Calendar*, *Contacts*, *Tasks*, etc.). Applies only to iPhone, Windows Mobile and Palm device types.
- Write Non-files to log the write access attempts for non-file objects (*Calendar, Contacts, Tasks*, etc.). Applies only to iPhone, Windows Mobile and Palm device types.
- **Copy** to log all attempts to paste data from the clipboard and capture screen shots. Applies only to the clipboard.
- **Shadowing** rights that belong to this group are responsible for actions logged into the shadow log.
  - Write to enable shadowing of all data written by the user. Applies only to DVD/CD-ROM, Floppy, iPhone, Parallel port, Removable, Serial port, Windows Mobile and Palm device types.
  - **Print** to enable shadowing of all documents sent to printers. Later, these documents can be viewed using the <u>DeviceLock Printer Viewer</u>. Applies only to the Printer device type.
  - Write Non-files to enable shadowing of all non-file objects (Calendar, Contacts, Tasks, etc.) written by the user. Applies only to iPhone, Windows Mobile and Palm device types.

Below you can see what audit rights can be assigned to what device types and what is written to the log. For all events DeviceLock Service logs event's type, date and time, device's type, user name and process information as well as the specific event's information described below:

DEVICE TYPE	RIGHTS
BlackBerry	<ul> <li>Audit: Read + Device Access action is written to the audit log.</li> <li>Audit: Write/Print + Device Access action is written to the audit log.</li> <li>Audit: Execute -</li> <li>Audit: Read Non-files -</li> <li>Audit: Write Non-files -</li> <li>Audit: Copy -</li> <li>Shadowing: Write/Print -</li> <li>Shadowing: Write Non-files -</li> </ul>

DEVICE TYPE	RIGHTS
Bluetooth	<ul> <li>Audit: Read + Device Access action is written to the audit log.</li> <li>Audit: Write/Print + Device Access action is written to the audit log.</li> <li>Audit: Execute - Audit: Read Non-files - Audit: Write Non-files -</li> <li>Audit: Copy -</li> <li>Shadowing: Write/Print -</li> <li>Shadowing: Write Non-files -</li> </ul>
Clipboard	<ul> <li>Audit: Read —</li> <li>Audit: Write/Print —</li> <li>Audit: Execute —</li> <li>Audit: Read Non-files —</li> <li>Audit: Write Non-files —</li> <li>Audit: Copy +</li> <li>Copy Text, Copy File, Copy Image, Copy Audio, Copy Unidentified, and Screenshot actions are written to the audit log.</li> <li>Shadowing: Write/Print —</li> <li>Shadowing: Write Non-files —</li> </ul>
DVD/CD-ROM	<ul> <li>Audit: Read +         Open, Device Access, Direct Access and Eject events, file names and flags (Read, DirectRead, Eject, DirList) write to the audit log.     </li> <li>Audit: Write/Print +         Open, Device Access and Direct Access events and flags (Write, Del, DirectWrite) write to the audit log.     </li> <li>Audit: Execute -         Audit: Read Non-files -         Audit: Write Non-files -         Audit: Copy -         Shadowing: Write/Print +         CD/DVD images in the CUE format and/or files write to the shadow log.         Shadowing: Write Non-files -         Shadowing: Write Non-files -         Shadowing: Write Non-files -         Shadowing: Write/Print +         CD/DVD images in the CUE format and/or files write to the shadow log.         Shadowing: Write Non-files -         Shadowing: Write Non-files -</li></ul>

DEVICE TYPE	RIGHTS
FireWire port	<ul> <li>Audit: Read + Insert, Remove and Device Access actions and device names write to the audit log.</li> <li>Audit: Write/Print + Insert, Remove and Device Access actions and device names write to the audit log.</li> <li>Audit: Execute –</li> <li>Audit: Read Non-files –</li> <li>Audit: Write Non-files –</li> <li>Audit: Copy –</li> <li>Shadowing: Write/Print –</li> <li>Shadowing: Write Non-files –</li> </ul>
Floppy	<ul> <li>Audit: Read +         <ul> <li>Open, Mount, Unmount and Direct Access actions, file names and flags (Read, DirectRead, Eject, DirList) write to the audit log.</li> </ul> </li> <li>Audit: Write/Print +         <ul> <li>Open, Open/Create, Overwrite/Create, Direct Access, Delete, Rename and Create new actions, file names and flags (Write, DirectWrite, Format, Del, DirCreate) write to the audit log.</li> <li>Audit: Execute —                 <ul></ul></li></ul></li></ul>
Hard disk	<ul> <li>Audit: Read +         Open, Mount, Unmount and Direct Access actions, file names and flags (Read, DirectRead, Eject, DirList) write to the audit log.     </li> <li>Audit: Write/Print +         Open, Open/Create, Overwrite/Create, Direct Access, Delete, Rename and Create new actions, file names and flags (Write, DirectWrite, Format, Del, DirCreate) write to the audit log.     </li> <li>Audit: Execute —         <ul> <li>Audit: Write Non-files —</li> <li>Audit: Copy —</li> <li>Shadowing: Write/Print —</li> </ul> </li> </ul>

DEVICE TYPE	RIGHTS
Infrared port	<ul> <li>Audit: Read + Device Access action writes to the audit log.</li> <li>Audit: Write/Print + Device Access action writes to the audit log.</li> <li>Audit: Execute -</li> <li>Audit: Read Non-files -</li> <li>Audit: Write Non-files -</li> <li>Audit: Copy -</li> <li>Shadowing: Write/Print -</li> <li>Shadowing: Write Non-files -</li> </ul>
iPhone	<ul> <li>Audit: Read + Read File action and file names write to the audit log.</li> <li>Audit: Write/Print + Write File, Rename File and Delete File actions and file names write to the audit log.</li> <li>Audit: Execute -</li> <li>Audit: Read Non-files + Read Calendar, Read Contact, Read Favorite, Read E-mail, Read Backup, Read Note and Read Media actions and object names write to the audit log.</li> <li>Audit: Write Non-files + Write Calendar, Delete Calendar, Write Contact, Delete Contact, Write Favorite, Delete Favorite, Write E-mail, Delete E-mail, Write Backup, Write Note, Delete Note, Write Media, Rename Media and Delete Media actions and object names write to the audit log.</li> <li>Audit: Copy -</li> <li>Shadowing: Write/Print + Files are written to the shadow log.</li> <li>Shadowing: Write Non-files + All data that contains non-file objects (Calendar, Contacts, etc.) is written to the shadow log.</li> </ul>

DEVICE TYPE	RIGHTS
Palm	<ul> <li>Audit: Read + Read File action, file names and the Sync flag write to the audit log.</li> <li>Audit: Write/Print + Write File action, file names and the Sync flag write to the audit log.</li> <li>Audit: Execute —</li> <li>Audit: Read Non-files + Read Calendar, Read Contact, Read Expense, Read E-mail, Read Document, Read Memo, Read Notepad, Read Task and Read Media actions and object names write to the audit log.</li> <li>Audit: Write Non-files + Write Calendar, Write Contact, Write Expense, Write E-mail, Write Document, Write Memo, Write Notepad, Write Task, Write Media and Install actions and object names write to the audit log.</li> <li>Audit: Copy —</li> <li>Shadowing: Write/Print + Files are written to the shadow log.</li> <li>Shadowing: Write Non-files + All data that contains non-file objects (Calendar, Contacts,</li> </ul>
Parallel port	<ul> <li>Tasks, etc.) is written to the shadow log.</li> <li>Audit: Read + <ul> <li>Device Access action writes to the audit log.</li> </ul> </li> <li>Audit: Write/Print + <ul> <li>Device Access action writes to the audit log.</li> </ul> </li> <li>Audit: Execute - <ul> <li>Audit: Read Non-files -</li> <li>Audit: Write Non-files -</li> <li>Audit: Copy -</li> <li>Shadowing: Write/Print + <ul> <li>All data sent to the port is written to the shadow log.</li> </ul> </li> <li>Shadowing: Write Non-files -</li> </ul> </li> </ul>
Printer	<ul> <li>Audit: Read —</li> <li>Audit: Write/Print + Print action, documents and printer names write to the audit log. </li> <li>Audit: Execute — <ul> <li>Audit: Read Non-files —</li> <li>Audit: Write Non-files —</li> <li>Audit: Copy —</li> <li>Shadowing: Write/Print + <ul> <li>All data sent to the printer is written to the shadow log in the native print spooler format.</li> <li>Shadowing: Write Non-files —</li> </ul> </li> </ul></li></ul>

DEVICE TYPE	RIGHTS
Removable	<ul> <li>Audit: Read + Open, Mount, Unmount and Direct Access actions, file names and flags (Read, DirectRead, Eject, DirList) write to the audit log. </li> <li>Audit: Write/Print + Open, Open/Create, Overwrite/Create, Direct Access, Delete, Rename and Create new actions, file names and flags (Write, DirectWrite, Format, Del, DirCreate) write to the audit log. </li> <li>Audit: Execute — <ul> <li>Audit: Read Non-files —</li> <li>Audit: Write Non-files —</li> <li>Shadowing: Write/Print + Files are written to the shadow log. </li> </ul> </li> </ul>
Serial port	<ul> <li>Audit: Read + Mount, Unmount, Insert, Remove and Device Access actions write to the audit log.</li> <li>Audit: Write/Print + Mount, Unmount, Insert, Remove and Device Access actions write to the audit log.</li> <li>Audit: Execute -</li> <li>Audit: Read Non-files -</li> <li>Audit: Write Non-files -</li> <li>Audit: Copy -</li> <li>Shadowing: Write/Print + All data sent to the port is written to the shadow log.</li> <li>Shadowing: Write Non-files -</li> <li>Shadowing: Write Non-files -</li> </ul>
Таре	<ul> <li>Audit: Read + Open, Device Access and Direct Access actions and flags (Read, DirectRead) write to the audit log.</li> <li>Audit: Write/Print + Open, Device Access and Direct Access actions and flags (Write, DirectWrite) write to the audit log.</li> <li>Audit: Execute - Audit: Read Non-files - Audit: Write Non-files - Audit: Copy - Shadowing: Write/Print - Shadowing: Write Non-files -</li> </ul>

DEVICE TYPE	RIGHTS
USB port	<ul> <li>Audit: Read + Insert, Remove and Device Access actions and device names write to the audit log.</li> <li>Audit: Write/Print + Insert, Remove and Device Access actions and device names write to the audit log.</li> <li>Audit: Execute –</li> <li>Audit: Read Non-files –</li> <li>Audit: Write Non-files –</li> <li>Audit: Copy –</li> <li>Shadowing: Write/Print –</li> <li>Shadowing: Write Non-files –</li> </ul>
WiFi	<ul> <li>Audit: Read + Device Access action writes to the audit log.</li> <li>Audit: Write/Print + Device Access action writes to the audit log.</li> <li>Audit: Execute —</li> <li>Audit: Read Non-files —</li> <li>Audit: Write Non-files —</li> <li>Audit: Copy —</li> <li>Shadowing: Write/Print —</li> <li>Shadowing: Write Non-files —</li> </ul>
Windows Mobile	<ul> <li>Audit: Read +         <i>Read File, Get File Attributes, Create New File, Overwrite/Create         File, Open File and Open/Create File actions, file names and flags         write to the audit log.         <ul> <li>Audit: Write/Print +                                    </li></ul></i></li></ul>
DEVICE TYPE	RIGHTS
-------------	---
	• Audit: Copy —
	Shadowing: Write/Print +
	Files are written to the shadow log.
	<ul> <li>Shadowing: Write Non-files +</li> </ul>
	All data that contains non-file objects (Calendar, Contacts, Tasks, etc.) is written to the shadow log.

**Note:** Until either **Audit Allowed** or **Audit Denied** is selected for the device type, logging to the audit log is disabled for that device in spite of defined audit rules.

Also logging to the audit log is disabled for devices that are in the white list and for a whole class of devices if the access control for that class is turned off in **Security Settings**.

# USB Devices White List (Regular Profile)

The devices white list allows you to authorize only specific devices that will not be locked regardless of any other settings. The intention is to allow special devices but lock all other devices.

File Action View Help ⇔ → € 100 13 12 12 13 10		
DeviceLock     DeviceLock Service     Service Options     Devices     Devices     Service Options     Devices     Devices     Devices     Devices     Devices     Devices     Devices     Devices     Devices	Description /	DeviceID USB\VID_04098PID_0040
TESTLABCK) administre     Media White List     Media White List     Content-Aware Rules     Security Settings     Audit Log Viewer     Shadow Log Viewer     DeviceLock Enterprise Server     DeviceLock Content Security Ser	Delete User Manage Manage Offline Load Load Offline Save Save Offline USB Devices Database View Export List Help	

Devices in the white list can be defined individually for every user and group. For more information on how the devices white list works, please read the <u>Managed</u> <u>Access Control</u> section of this manual.

**Note:** Audit is not performed for users' attempts to access a whitelisted device while users' attempts to insert or remove a whitelisted device are audited.

There are two ways to identify devices in the white list:

- Device Model represents all devices of the same model. Each device is identified by a combination of Vendor Id (VID) and Product Id (PID). This combination of VID and PID describes a unique device model but not a unique device unit. It means that all devices belonging to the certain model of the certain vendor will be recognized as the one authorized device.
- Unique Device represents a unique device unit. Each device is identified by a combination of Vendor Id (VID), Product Id (PID) and Serial Number (SN). Not all devices have serial numbers assigned. A device can be added to the white list as a Unique Device only if its manufacturer has assigned a serial number to it at the production stage.

Two steps are required to authorize a device:

- 1. Add the device to the <u>devices database</u>, making it available for adding to the white list.
- 2. Add the device to the white list for the specified user/group. In effect, this designates the device as authorized and allows it for this user/group at the interface (USB) level.

**Note:** You can define different online vs. offline USB Devices White Lists for the same user or sets of users. The online USB Devices White List (Regular Profile) applies to client computers that are working online. The offline USB Devices White List (Offline Profile) applies to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define the offline USB Devices White List, see "Managing Offline USB Devices White List."

To define the online (regular) white list, select **Manage** from the context menu available with a right mouse click. Alternatively, you can press the appropriate button on the toolbar.

DB Devices White List				
ISB Devices Database				
Description	DeviceID	Туре		
Lexar Flash Drive	USBWID_007D&PID_14	40 Unique Device		
🔁 Mini Flash	USBWID_090AMPID_10	01 Device Model		
			Charac	ART
Add US8 Devices Database			Show.	All Types
Users	Description	DeviceID	Reinitialize	Туре
Users	Description	DeviceID	Reinitialize	Туре
VM2000AD VAdministrator	Lexar Flash Drive	USBWID_0D7D&PID_1400\073C1B300351	×	Unique Device
27VM2000AD1Domain Users				
Add Delete	Delete Edit		L	oad Save
Add Delete	Delete Edit			oad Save
Add Delete	Delete Edit			sad Save

In the **USB Devices Database** list at the top of the dialog box, you can see devices that were added to the database.

Once devices are added from the database to the white list of a certain user, they become authorized devices for which access control is disabled when this user is logged in.

You can add a device to the USB Devices White List in two steps:

- Select a user or user group for which this device should be allowed. Click Add under the Users list to add the user/group. To delete the record from the Users list, click Delete.
- 2. Select the appropriate device record in the **USB Devices Database** list and click **Add**.

If the device has an assigned serial number, it can be added to the white list two times: as Device Type and as Unique Device. In this case Device Type has a priority over Unique Device.

When the **Control as Type** check box is selected, access control for white listed devices is disabled only on the interface (USB) level. If the white listed device (for example, USB Flash Drive) belongs to both levels: interface (USB) and type (Removable), the permissions (if any) for the type level will be applied anyway.

Otherwise, if the **Control as Type** check box is not selected, access control on the type level is also disabled. For example, by clearing the **Control as Type** check box for the USB Flash Drive, you can bypass security checking on the Removable level.

**Note:** When you add a USB composite device (a device that is represented in the system by a parent composite device and one or more child interface devices) to the USB Devices White List, consider the following:

If you add any device of a USB composite device to the white list, access control is disabled for all devices of the composite device at the interface (USB port) level. If the white-listed device belongs to both levels: interface (USB) and type (for example, Removable) and the **Control as Type** check box is selected, the permissions (if any) for the type level will be applied anyway.

If it is necessary to force the white listed device to reinitialize (replug) when the new user is logged in, select the **Reinitialize** check box.

Some USB devices (like the mouse) will not work without being reinitialized, so it is recommended to keep this check box selected for non-storage devices.

It is recommended to keep the **Reinitialize** check box unselected for storage devices (such as flash drives, CD/DVD-ROMs, external hard drives and so on).

Some USB devices cannot be reinitialized from DeviceLock Service. It means that their drivers do not support the software replug. If such a device was white listed but

does not work, the user should remove it from the port and then insert it again manually to restart the device's driver.

To edit a device's description, select the appropriate record in **USB Devices White List** and click **Edit**.

Click **Delete** to delete a selected device's record (use CTRL and/or SHIFT to select several records simultaneously).

To save the white list to an external file, click **Save**, and then select the name of the file. To load a previously saved white list, click **Load** and select a file that contains the list of devices.

If you need to manage the <u>devices database</u>, you can click **USB Devices Database** and open the appropriate dialog box.

**Note:** If you add an iPhone device to the USB Devices White List, access control is disabled for both the iPhone and its camera at the interface (USB port) level. Thus, you cannot allow access to iPhone and deny access to its camera at the interface (USP port) level. In the USB devices database, an iPhone device is identified as the "Apple Mobile Device USB Driver."

However, it is possible to allow access to iPhone's camera and deny access to iPhone. To do this, you can use any of the following methods:

Method 1. To allow access to iPhone's camera, add the iPhone to the USB Devices White List and select the **Control as Type** check box. To deny access to iPhone, set the No Access permission for the **iPhone** device type.

Method 2. To allow access to iPhone's camera, clear the **Access control for USB scanners and still image devices** check box in **Security Settings**. To deny access to iPhone, set the No Access permission for the **USB port** device type.

### **USB** Devices Database

In the **USB Devices Database** dialog box you can add new devices to the database and edit existing records.

USB Devices Database				?
	Available USB Devices	(xpvirt):		
Description	C DeviceID		Present	
🕂 USB Mass Storage De	vice (Device Model) USB\VID_090A&PI	ID_1001		
🖃 🔁 USB Mass Storage De	vice (Device Model) USB\VID_0D7D&P	4D_1400		
Storage Wass Storage	Device USBWID_0D7D&P	PD_1400\073C1B300351	Yes	
Add Expand All	Collapse All	Remote Computer	Show all devices	Refresh
	USB Devices Databa	ase:		
Description	DeviceID	Tune		
A aver Elack Drive	USRIVID 0D7DtRID 1400	072C1P200251 Upique	Device	
A CONDITIONTOTIVO	0301110_007010_1400	torocrosocosi onique	DOVIDO	
	1			1 .
Delete		Show: All Types	<ul> <li>Load</li> </ul>	Save
		OK	Cancel	Apply
				and the second s

Before the device can be authorized in the <u>white list</u>, it must be added to the database.

In the **Available USB Devices** list at the top of the dialog box, you can see all devices available on the computer.

Devices are displayed in the form of a simple tree, where the parent item represents **Device Model** and the child item represents **Unique Device**. If there is no Unique Device item, then this device does not have an assigned serial number.

This list displays either all currently plugged-in devices (if the **Show all devices** button is not clicked) or all the devices ever plugged into the port on this computer (if the **Show all devices** button is clicked).

The list of available devices is automatically refreshed and displays new devices as soon as they arrive. To manually refresh this list, click **Refresh**.

To retrieve devices from the remote computer, click **Remote Computer**. This button is unavailable when you are connected to the local computer.

In the **USB Devices Database** list at the bottom of the dialog box, you can see devices that are already in the database.

You can add devices to this list by selecting the desired device's record in the **Available USB Devices** list and clicking **Add**. If the device is already in the database, it cannot be added there a second time.

To edit a device description, select the appropriate record in the **USB Devices Database** list and click **Edit**.

Click **Delete** to delete a selected device's record (press CTRL and/or SHIFT to select several records simultaneously).

You can also save a current database to an external file. To save the database to an external file, click **Save**, then select the type of the file —.txt or .csv.

To load a previously saved database, click **Load** and select a file that contains the list of devices.

# Media White List (Regular Profile)

The media white list allows you to uniquely identify a specific DVD/CD-ROM disk by the data signature and authorize read access to it, even when DeviceLock Service has otherwise blocked DVD/CD-ROM drives.



The media white list can be configured to grant access to a collection of approved DVD/CD-ROM disks by certain users and groups, so that only authorized users are able to use the approved information.

Any change to the content of the media will change the data signature, thus invalidating authorization. If the user copies the authorized media without any changes in the original content (byte-to-byte copy) then such a copy is accepted as the authorized media.

**Note:** Access to white listed media can be granted only on the type (DVD/CD-ROM) level. If the DVD/CD drive plugs into the port (USB or FireWire) and access to this port is denied, then access to the white listed media is denied too.

Two steps are required to authorize media:

- 1. Add the media to the <u>media database</u>, making it available for adding to the white list.
- 2. Add the media to the white list for the specified user/group. In effect, this designates the media as authorized and allows it (read access) for this user/group at the type (DVD/CD-ROM) level.

**Note:** You can define different online vs. offline Media White Lists for the same user or sets of users. The online Media White List (Regular Profile) applies to client computers that are working online. The offline Media White List (Offline Profile) applies to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define the offline Media White List, see "Managing Offline Media White List."

To define the online (regular) media white list, select **Manage** from the context menu available with a right mouse click. Alternatively, you can press the appropriate button on the toolbar.

🗟 Media White List			
Media Database			
Description	MedialD	Туре	
MSDA35	848C7078092681DC095D6F344E68422D	DVD/CD-ROM	
SQLENTSEL	42F99FABE1717CB7C39D6E23C442A7A9	DVD/CD-ROM	
Add Mode Database			
Add Media Database			
Media White List	Media		
Users	Description MedialD		Туре
2 xpvirt\Administrators	SQLENTSEL 42F99FABE1717C	87C39D6E23C442A7A9	DVD/CD-ROM
2 VM2000AD\Guest			
Add Delete	Edit		Load Save
		ОК	Cancel Apply

In the **Media Database** list at the top of the dialog box, you can see all media that were added to the database.

Once media are added from the database to the white list of a certain user, they become authorized media for which access control is disabled when this user is logged in.

You can add media to the Media White List in two steps:

- Select a user or user group for which this media should be allowed. Click Add under the Users list to add the user/group. To delete the record from the Users list, click Delete.
- 2. Select the appropriate media record in the **Media Database** list and click **Add**.

To edit a media's description, select the appropriate record in **Media White List** and click **Edit**. Click **Delete** to delete a selected media's record (use CTRL and/or SHIFT to select several records simultaneously).

To save the media white list to an external file, click **Save**, then select the name of the file.

To load a previously saved white list, click **Load** and select a file that contains the list of medias.

If you need to manage the <u>media database</u>, you can click **Media Database** and open the appropriate dialog box.

**Note:** Using the media white list you can only allow read access to authorized media. It is impossible to authorize media for writing.

### Media Database

In the **Media Database** dialog box you can add new media to the database and edit existing records.

Media Database				×
	Drives:			
Drive	Туре	Volume Name		
a∰D:	DVD/CD-ROM	SQLENTSEL		
a E: (No Media)	DVD/CD-ROM			
Add Eject	Load			Refresh
Description	MedialD		Туре	
SQLENTSEL	42F99FABE1717CB7C3	39D6E23C442A7A9	DVD/CD-ROM	
Delete Edit			Load	Save
		OK	Cancel	Apply

Before the media can be authorized in the <u>white list</u>, it must be added to the database.

In the **Drives** list at the top of the dialog box, you can see all drives available on the local computer that can contain medias.

The list is automatically refreshed and displays new medias as soon as they arrive. To manually refresh this list, click **Refresh**.

In the list at the bottom of the dialog box, you can see media that are already in the database.

You can add media to this list by selecting the desired record in the **Drives** list and clicking **Add**. It takes some time (depending on the media size) to authorize the media. If the media is already in the database, it cannot be added there a second time.

To edit a media description, select the appropriate record in the list and click **Edit**.

Click **Delete** to delete a selected record (use CTRL and/or SHIFT to select several records simultaneously).

You can also save a current database to an external file. To save the database to an external file, click **Save**, then select the type of the file —.txt or .csv.

To load a previously saved database, click **Load** and select a file that contains the list of medias.

# Security Settings (Regular Profile)

There is a list of additional security parameters that affect permissions and audit rules for some device types.

Ele Action Yew Help ← → € 🐻 🗟 🕄 🗑 😏	1		
	Name Access control for USB HID (mouse, keyboard, etc.) Access control for USB printers Access control for USB Buetooth adapters Access control for USB scanners and still image devices Access control for USB scanners and still image devices Access control for USB scanners and still image devices Access control for USB scanners and still image devices Access control for USB scanners and still image devices Access control for USB scanners and still image devices Access control for rules broage devices Access control for rules broage devices Access control for ritual printers (Windows 2000 and later) Access control for vitual printers (Windows 2000 and later) Access control for Clipboard data within one process Block FireWire controller if access is denied	Regular Disabiled Enabled Enabled Enabled Enabled Enabled Enabled Enabled Disabiled Disabiled	Offline Not Configured Not Configured

These security parameters enable you to keep some device types completely locked, but allow the use of certain device classes without need to authorize every device in the white list.

For example, you can disallow using all USB devices except any mouse and keyboard devices that connect through the USB.

DeviceLock supports these additional security parameters:

- Access control for USB HID if enabled, allows DeviceLock Service to audit and control access to Human Interface Devices (mouse, keyboard, and so on) plugged into the USB port. Otherwise, even if the USB port is locked, Human Interface Devices continue to function as usual and audit is not performed for these devices.
- Access control for USB printers if enabled, allows DeviceLock Service to audit and control access to printers plugged into the USB port. Otherwise, even if the USB port is locked, printers continue to function as usual and audit is not performed for these devices.
- Access control for USB scanners and still image devices if enabled, allows DeviceLock Service to audit and control access to scanners and still image devices plugged into the USB port. Otherwise, even if the USB port is locked, these devices continue to function as usual and audit is not performed for these devices.
- Access control for USB Bluetooth adapters if enabled, allows DeviceLock Service to audit and control access to Bluetooth adapters plugged into the USB port. Otherwise, even if the USB port is locked, Bluetooth

adapters continue to function as usual and audit is not performed for these devices.

This parameter affects audit and access control on the interface (USB) level only. If the device belongs to both levels, the permissions and audit rules (if any) for the type (Bluetooth) level will be applied anyway.

 Access control for USB storage devices – if enabled, allows DeviceLock Service to audit and control access to storage devices (such as flash drives) plugged into the USB port. Otherwise, even if the USB port is locked, storage devices continue to function as usual and audit is not performed for these devices.

This parameter affects audit and access control on the interface (USB) level only. If the device belongs to both levels: interface and type, the permissions and audit rules (if any) for the type (Removable, Floppy, DVD/CD-ROM or Hard disk) level will be applied anyway.

- Access control for USB and FireWire network cards if enabled, allows DeviceLock Service to audit and control access to network cards plugged into the USB or FireWire (IEEE 1394) port. Otherwise, even if the USB or FireWire port is locked, network cards continue to function as usual and audit is not performed for these devices.
- Access control for FireWire storage devices if enabled, allows DeviceLock Service to audit and control access to storage devices plugged into the FireWire port. Otherwise, even if the FireWire port is locked, storage devices continue to function as usual and audit is not performed for these devices.

This parameter affects audit and access control on the interface (FireWire) level only. If the device belongs to both levels: interface and type, the permissions and audit rules (if any) for the type (Removable, Floppy, DVD/CD-ROM or Hard disk) level will be applied anyway.

- Access control for serial modems (internal & external) if enabled, allows DeviceLock Service to audit and control access to modems plugged into the COM port. Otherwise, even if the COM port is locked, modems continue to function as usual and audit is not performed for these devices.
- Access control for virtual CD-ROMs if enabled, allows DeviceLock Service to audit and control access to virtual (software emulated) CD-ROMs. Otherwise, even if the CD-ROM device is locked, virtual drives continue to function as usual and audit is not performed for these devices. This parameter is effective only for Windows 2000 and later systems.
- Access control for virtual printers if enabled, allows DeviceLock Service to audit and control access to virtual printers which do not send documents to real devices, but instead print to files (for example, PDF converters). Otherwise, even if the physical printer is locked, virtual printers continue to print as usual and audit is not performed for them. This parameter is effective only for Windows 2000 and later systems.

- Access control for inter-application copy/paste clipboard operations if enabled, allows DeviceLock Service to audit and control access to copy/paste operations between different applications. Otherwise, even if the clipboard is locked, access control for copy/paste operations between different applications is disabled and audit is not performed for them.
- **Block FireWire controller if access is denied** if enabled, allows DeviceLock Service to disable FireWire controllers when the Everyone account has No Access permissions for the FireWire port device type.

**Note:** You can define different online vs. offline Security Settings for the same user or sets of users. Online Security Settings (Regular Profile) apply to client computers that are working online. Offline Security Settings (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define offline Security Settings, see "Managing Offline Security Settings."

To change online (regular) security parameters, double-click the parameter's record to switch its state (**enable/disable**). Alternatively, you can select **Manage** from the context menu available with a right mouse click or press the appropriate button on the toolbar.

🕵 Security Settings 🛛 🔹 💽
Access control for USB HID (mouse, keyboard, etc.)  Access control for USB printers Access control for USB Bluetooth adapters Access control for USB and FireWire network cards Access control for USB scanners and still image devices Access control for USB storage devices Access control for USB storage devices Access control for VISB storage devices Access control for VISB storage devices Access control for FireWire storage devices Access control for Vitual DVD/CD-ROMs (Windows 2000 and later) Access control for vitual printers (Windows 2000 and later) Access control for Vitual printers (Windows 2000 and later) Access control for Clipboard data within one process Block FireWire controller if access is denied
OK Cancel

Security Settings are similar to the <u>device white list</u> but there are three major differences:

1. Using Security Settings you can only allow a whole class of device. You cannot allow only a specific device model, while locking out all other devices of the same class.

For example, by disabling **Access control for USB storage devices**, you allow the use of all USB storage devices, no matter their model and vendor. By specifying the one USB Flash Drive model you want to allow on the devices white list, you ensure that all other USB storage devices remain locked out.

2. Using Security Settings you can only select from the predefined device classes. If the device does not belong to one of the predefined classes, then it cannot be allowed.

For example, there is no specific class for smart card readers in Security Settings, so if you want to allow a smart card reader when the port is locked, you should use the devices white list.

3. Security Settings cannot be defined on a per-user basis; they affect all users of the local computer. However, devices in the white list can be defined individually for the every user and group.

**Note:** Security Settings work only for those devices that are using standard Windows drivers. Some devices are using proprietary drivers and their classes cannot be recognized by DeviceLock Service. Hence, access control to such devices cannot be disabled via Security Settings. In this case you may use the <u>devices white list</u> to authorize such devices individually.

# Audit Log Viewer (Service)

There is a built-in audit log viewer that allows you to retrieve DeviceLock audit log records from a computer's local Windows event logging subsystem.

The standard Windows event logging subsystem is used to store audit records, only if **Event Log** or **Event & DeviceLock Logs** is selected in the **Audit log type** parameter in <u>Service Options</u>. Otherwise, audit records are stored in the proprietary log and can be viewed using the <u>server's audit log viewer</u>.

JeviceLock Manageme	nt Console					×
File Action View Help ← →  €	2 🖬 🔊 🖬 🕽	< 🕄 ⊽⊨ -				
DeviceLock		Туре	Date/Time 🗸	Source	Action	^
Construction     Construction	al, WIN/PPROSP3	Success Success Success Success	12/13/2010 8:32:5 12/13/2010 8:32:1 12/13/2010 7:53:3 12/13/2010 7:51:2	Service Service Service Service	Started Stopped Started Shutdown	
Bodow Log View     Shadow Log View     DeviceLock Enterprise     DeviceLock Content 5	Settings Save Clear Refresh Filter Send Data to Serv View	coess coess coess coess coess coess coess coess	12/13/2010 7:46:3 12/13/2010 7:43:0 11/30/2010 10:16: 11/30/2010 6:50:1 11/29/2010 4:50:2 11/29/2010 4:50:1 11/29/2010 4:50:1	Service Service Service Service Service Service	Started Shutdown Set Protocols White List Set Content-Aware Rules (Protocols) Set Audit & Shadow Options Set Audit & Shadow Options Set Audit & Shadow Options	
<	Export List		11/27/2010 2:20/011	2017100	Set set the optimis	ř
Exports the current list to a file	Help					

The audit log stores events generated by a user's device-related activities that fall under the audit rules. For more information, please read the <u>Auditing & Shadowing</u> <u>section</u> of this manual.

Also, changes in a DeviceLock Service's configuration generate events in the audit log, if the appropriate check box is selected in <u>Service Options</u>.

The columns of this viewer are defined as follows:

- **Type** the class of an event, either **Success** for allowed access or **Failure** for denied access.
- **Date/Time** the date and the time when an event was received by DeviceLock Service.
- **Source** the type of device or protocol involved.
- Action the user's activity type.
- Name the name of the object (file, USB device, etc.).
- **Information** other device-specific information for the event, such as the access flags, devices names, and so on.
- **User** the name of the user associated with this event.
- **PID** the identifier of the process associated with this event.
- **Process** the fully qualified path to the process executable file. In some cases, the process name may be displayed instead of the path.

To refresh the list of events, select **Refresh** from the context menu available by a right mouse click or press the appropriate button on the toolbar.

To clear all events from the audit log, select **Clear** from the context menu or press the appropriate button on the toolbar.

### Audit Log Settings (Service)

To define a maximum log size and what Windows should do if the audit log becomes full, use **Settings** from the context menu of **Audit Log Viewer** or press the appropriate button on the toolbar.

DeviceLock Audit Log Setting	: ? 🛛
Log size	
Maximum log size: 512	КВ
When maximum log size is reache	d:
Overwrite events as needed	
<ul> <li>Overwrite events older than</li> </ul>	7 🛟 days
O Do not overwrite events (clear log manually)	Restore Defaults
	OK Cancel

In the **Maximum log size** parameter, you can specify the maximum size of the log file (in kilobytes). The log file is created and used only by the Windows Event Log service. This file is usually located in the **%SystemRoot%\system32\config** directory and has the **DeviceLo.evt** name.

To specify what Windows should do when an event log is full (when Maximum log size is reached) select one of these options:

- **Overwrite events as needed** the system will overwrite old events if Maximum log size is reached.
- **Overwrite events older than** specifies that records that are newer than this value will not be overwritten (specified in days).
- Do not overwrite events (clear log manually) the system will not overwrite old events if Maximum log size is reached and you will need to clear events manually.

**Note:** When the event log is full and there are no records that Windows can overwrite, then DeviceLock Service is unable to write new audit records to this log.

If you wish to reset current settings to the default values, click **Restore Defaults**. Default values are:

- The Maximum log size parameter is set to 512 kilobytes.
- The **Overwrite events older than** option is selected and set to 7 days.

#### Audit Log Filter (Service)

You can filter data in <u>Audit Log Viewer</u> so that only records that meet specific conditions are displayed in the list.

To open the **Filter** dialog box, use **Filter** from the context menu of **Audit Log Viewer** or press the appropriate button on the toolbar.

lter			?			
Even S	Exclude types uccess ar	ıdit	✓ Failure audit			
Name: Source		Remov	vable 🗸			
Action		Delete 💌				
Informa User:	tion:	Guest				
Process	ĸ		PID:			
From:	Events	Dn 🔽	12/ 1/2010 🛛 6:41:21 AM 📚			
To:	Events	On 🔽	12/31/2010 💌 6:41:21 AM 🗘			
🗹 Ena	ble filter		Load Save			
			OK Cancel			

There are two types of filters:

- **Include** only entries that match conditions specified on the **Include** tab are shown in the list.
- **Exclude** entries that match conditions specified on the **Exclude** tab are not shown in the list.

To use any filter, you should activate it first. Select the **Enable filter** check box to make a filter active. To temporary deactivate the filter, clear the **Enable filter** check box.

When the filter is active you can define its condition by entering values into the following fields:

- **Success audit** specifies whether to filter device access attempts that were successful.
- Failure audit specifies whether to filter device access attempts that failed.
- **Name** the text that matches a value in the Audit Log Viewer's **Name** column. This text is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- **Source** the text that matches a value in the Audit Log Viewer's **Source** column. This text is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- **Action** the text that matches a value in the Audit Log Viewer's **Action** column. This text is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- Information the text that matches a value in the Audit Log Viewer's Information column. This text is not case-sensitive and you may use wildcards.

You can enter multiple values separated by a semicolon (;).

- **User** the text that matches a value in the Audit Log Viewer's **User** column. This text is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- **Process** the text that matches a value in the Audit Log Viewer's **Process** column. This text is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- PID the number that matches a value in the Audit Log Viewer's PID column.
   You can enter multiple values constanted by a comission (:)

You can enter multiple values separated by a semicolon (;).

 From – specifies the beginning of the interval of events that you want to filter. Select First Event to see events starting with the first event recorded in the log. Select Events On to see events that occurred starting with a specific time and date. To – specifies the end of the range of events that you want to filter. Select
 Last Event to see events ending with the last event recorded in the log.
 Select Events On to see events that occurred ending with a specific time and date.

The AND logic is applied to all specified fields and between active filters (Include/Exclude). It means that the filter's result includes only those records that comply with all defined conditions.

If you do not want to include a field to the filter's condition, just leave this field empty.

For some fields you can use wildcards. A wildcard is a character such as an asterisk (\*) or a question mark (?) that is used to represent one or more characters when you are defining a filter.

Use the asterisk as a substitute for zero or more characters. If you are looking for a name that you know starts with "win" but you cannot remember the rest of the name, type the following: **win\***. This locates all names that begin with "win" including Windows, Winner, and Wind.

Use the question mark as a substitute for a single character in a name. For example, if you type **win?**, you will locate Wind but not Windows or Winner.

# Shadow Log Viewer (Service)

There is a built-in shadow log viewer that allows you to retrieve the shadow log from DeviceLock Service.

Jevi 🗸	ceLock Management Cons	sole					
File A ⇐ →	ction View Help	© ⊽= -					
I Devic	:eLock		Status	Date/Time	Source	Action	File Name /
Control Contro Control Control Control Control Control Control Control Control Co		PPROSP3	Success 12/16/2010 7:	Removable Writ Removable Writ	Write Write	Open Save Save As Raw Data Delete View External Viewer	
	eviceLock Content Security Ser	ver	<	El			Refresh Filter Send Data to Server Help

The typical DeviceLock configuration assumes that the shadow data is stored on DeviceLock Enterprise Server. In this case all shadow data which is originally logged and cached by DeviceLock Service on the local computer is periodically moved to the server. The local shadow log is cleared as soon as the data is successfully moved to the server, so to view this data, you should use the <u>server's shadow log viewer</u>.

However, in some cases you may need to view the shadow log of a certain computer. This need arises when, for example, you do not use DeviceLock Enterprise Server at all or when the server is being used, but for some reason the data still exists on the client computer.

The columns of this viewer are defined as follows:

- Status indicates the status of the record. The Success status indicates that data is successfully logged; the Incomplete status indicates that data is possibly not completely logged while the Failed status is given to shadow copies of files whose transmission was blocked by Content-Aware Rules.
- **Date/Time** the date and the time when the data was transferred.
- Source the type of device or protocol involved.
- Action the user's activity type.
- **File Name** the original path to the file or the auto-generated name of the data that originally was not a file (such as CD/DVD images, data written directly to the media or transferred through the serial/parallel ports).
- **File Size** the size of the data.
- **User** the name of the user transferred the data.
- **PID** the identifier of the process used to transfer the data.
- **Process** fully qualified path to the process executable file. In some cases, the process name may be displayed instead of the path.

Use the context menu available via a right mouse click on every record.

#### Open

To open the file from a selected record with its associated application, use **Open** from the context menu. If there is no associated application then the '**Open With**' dialog box is shown. In case the record has no associated data (its size is 0 or it was not logged), **Open** is disabled.

If you use **Open** for shadowing data captured from either Printer or Parallel port device types then the associated application is always the built-in viewer called DeviceLock Printer Viewer.

DeviceLock Printer Viewer is able to show you the shadowed printed document in the native print spooler format, send it to the printer again, or save it as a graphic file (such as BMP, GIF, JPEG, PNG, EMF or TIFF). Next print spooler formats are supported: PostScript, PCL5, PCL6 (PCL XL), HP-GL/2, GDI printing (ZjStream) and EMF Spooled Files.

#### Save

If you need to save data from a selected record to your local computer, use **Save** from the context menu or press the appropriate button on the toolbar.

Use CTRL and/or SHIFT to select and save the data from several records simultaneously.



In case the record has no associated data (its size is 0 or it was not logged), **Save** is disabled in the context menu and on the toolbar.

The progress bar appears when you are saving a large file.



You can click **Cancel** at any time to abort the saving process. In this case the resultant file on the local computer will be incomplete and will contain only that part of the data which was received before you aborted the saving process.

If the data was transferred by the user as a file, it is stored in the shadow log as a file and can be saved to the local computer as a file too.

When a user has written data to a CD/DVD disk, all data is stored in a shadow log as a single CD/DVD image (one image per each written CD/DVD disk or session) in the CUE format.

CD/DVD images as well as other data that originally was not transferred as files (direct media access or serial/parallel ports transfer) have auto-generated names

based on the action's type, drive's letter or device's name and time/date (for example, direct\_write(E:) 19:18:29 17.07.2006.bin).

Each CD/DVD image is saved to the local computer as two files: the data file with the .bin extension (for example, direct\_write(E\_)  $19_18_29 17_07_2006.bin$ ) and the cue sheet file that has the same name as its data file with the .cue extension (for example, direct\_write(E\_)  $19_18_29 17_07_2006_{bin.cue}$ ). These both files are necessary to open the CD/DVD image in the external application that supports the CUE format (such as Cdrwin, Nero, DAEMON Tools, IsoBuster, UltraISO, WinISO and many others).

### Save As Raw Data

When you select a record that contains the data originally written as an additional session to a multi-session CD/DVD disk, the **Save As Raw Data** item is available in the context menu. It allows you to save the data to the local computer as is (without fixing references to the data in previous sessions).

If you are using the regular saving function (the **Save** command or the toolbar's button), DeviceLock Management Console detects that the CD/DVD image contains a session that refers to the data in other (previous) sessions. Since the previous sessions are not available (they could be written on the computer where DeviceLock Service is not installed), DeviceLock Management Console locates and fixes all references to these non-existent sessions to make the .cue file readable by applications that support this format.

However, if you need to get the data that was not modified by DeviceLock Management Console, use **Save As Raw Data**. In this case the resultant file may be unreadable by applications that support the CUE format.

When saving large files, you can click the **Cancel** button on the progress bar to abort the saving process. In this case the resultant file on the local computer will contain only that part of the data which was received before you aborted the saving process.

#### View

To open the data in the built-in viewer, use **View** from the context menu.

📼 restart service.bat	×
"C:\Program Files\DeviceLock\dlservice.exe" -e pause "C:\Program Files\DeviceLock\dlservice.exe" -s	
C Hex (* Autodetect Text C ANSI Text C UTF-16 Text C UTF-16bb Text	Save Close

In the built-in viewer, click any of the following viewing options:

- **Hex** Displays data in hex as well as in words.
- **Autodetect Text** Enables the auto-detection of encoding for text and displays data in textual format only.
- **ANSI Text** Specifies ANSI encoding for text and displays data in textual format only.
- **UTF-16 Text** Specifies Unicode UTF-16 encoding for text and displays data in textual format only.
- **UTF-16BE Text** Specifies Unicode UTF-16 (Big Endian) encoding for text and displays data in textual format only.

When you are opening the large file, you can click **Cancel** on the progress bar to abort the opening process.

Please Wait [13%]	
Saving file C:\DOCUME~1\ADMINI~1.VM2\LOCAL5~1\Temp\dlm16.tmp	
Cancel	כ

In this case the viewer will show only that part of the data which was received before you aborted the opening process.

Click **Save** to save the data from the viewer to an external file.

#### **External Viewer**

Also, you can define the external program that will be used to view the shadow data.

If such an external application is defined, **External Viewer** is available on the shortcut menu. To define it, open **Regedit** and set the following entry on the computer where DeviceLock Management Console is running:

- Key: HKEY\_CURRENT\_USER\Software\SmartLine Vision\DLManager\Manager
- Name: ExternalShadowViewer
- Type: **REG\_SZ**
- Value: <full\_path\_to\_viewer> %1

where <*full\_path\_to\_viewer*> must be replaced by the full path to the external application. If this path contains spaces, use quotation marks. For example: "C:\Program Files\Microsoft Office\OFFICE11\winword.exe" %1.

When you are opening a large file, you can click **Cancel** on the progress bar to abort the opening process. In this case the external application will receive only that part of the data which was received before you aborted the opening process.

#### Delete

To delete a record, select **Delete** from the context menu or press the appropriate button. Use CTRL and/or SHIFT to select and remove several records simultaneously.

#### Refresh

To refresh the list, select **Refresh** from the context menu available via a right mouse click or press the appropriate button on the toolbar.

#### Send Data to Server

When DeviceLock Enterprise Server is defined in <u>Service Options</u> and you need to force moving the shadow data from the current computer to the server, use **Send Data to Server** from the context menu available by a right mouse click or press the appropriate button on the toolbar.

#### Shadow Log Filter (Service)

You can filter data in <u>Shadow Log Viewer</u> so that only records that meet certain conditions are displayed in the list.

To open the **Filter** dialog box, use **Filter** from the context menu of **Shadow Log Viewer** or press the appropriate button on the toolbar.

<b>v</b> s	luccess		V Ir	complete	,	🗹 Fa	ailed
File Na	me:	*databa	se*				
Source	¢	Removable					
Action							
User:		"\guest					
Proces	s:					PID:	
Files	ize						
File s	ize Ieen 🔽	1		and 80		GB	~
File s Betw From:	ize Ieen 🔽 Record	1 : On 🔽	12/	and 80	~	GB 1:03:31	

There is no big difference between defining Audit Log Filter and Shadow Log Filter, so first read the <u>Audit Log Filter (Service)</u> section of this manual.

When the filter is active you can define its condition by entering values into the following fields:

- **Success** specifies whether to filter the successfully logged data.
- **Incomplete** specifies whether to filter the data that was logged incompletely.
- **Failed** specifies whether to filter the logged data whose transmission was blocked by Content-Aware Rules.
- File Name the text that matches a value in the Shadow Log Viewer's File Name column. This text is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- Source the selection that matches a value in the Shadow Log Viewer's Source column.

You can enter multiple values separated by a semicolon (;).

 Action – the selection that matches a value in the Shadow Log Viewer's Action column.

You can enter multiple values separated by a semicolon (;).

• **User** – the text that matches a value in the Shadow Log Viewer's **User** column. This text is not case-sensitive and you may use wildcards.

You can enter multiple values separated by a semicolon (;).

- **Process** the text that matches a value in the Shadow Log Viewer's **Process** column. This text is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- **PID** the number that matches a value in the Shadow Log Viewer's **PID** column.

You can enter multiple values separated by a semicolon (;).

- **File size** the number or the region of numbers that matches a value in the Shadow Log Viewer's **File Size** column.
- **From** specifies the beginning of the interval of records that you want to filter. Select **First Record** to see records starting with the first record written to the log. Select **Records On** to see records that were written starting with a specific time and date.
- To specifies the end of the range of records that you want to filter. Select
  Last Record to see records ending with the last record written to the log.
  Select Records On to see records that were written ending with a specific
  time and date.

# Managing DeviceLock Enterprise Server

Expand the **DeviceLock Enterprise Server** item to get access to all of a server's functions and configuration parameters.

SeviceLock Management Console	
File Action View Help ← → € ■ ₽ ₽ ₽ ■ ■	
DeviceLock Service (Local, WINXPPROSP3     DeviceLock Enterprise Server     Conne	Server Options
Content Security S     Reconned     Certific     DeviceLock Content Security S     Reconned     Certific     DeviceL     About D     View	ect t to Last Used Server at Startup ate Generation Tool .ock Signing Tool DeviceLock
Export	List
Help	
	Local Computer

There is a context menu available by a right mouse click on the **DeviceLock Enterprise Server** item:

Connect – connects to any computer that you specify. For more information please read the <u>Connecting to Computers</u> section of this manual.
 When you connect to a computer where an old version of DeviceLock Enterprise Sever is installed, you may receive the following message.



In this case you need to install the new version DeviceLock Enterprise Server on this computer. For information on how to install DeviceLock Enterprise Server, please read the <u>Installing DeviceLock Enterprise Server</u> section of this manual.

- **Reconnect** connects to the currently connected computer once again.
- **Connect to Last Used Server at Startup** check this flag to instruct DeviceLock Management Console to automatically connect to the last used server each time console starts up.
- **Certificate Generation Tool** runs the special tool that allows you to generate DeviceLock Certificates. For more information please read the <u>Generating DeviceLock Certificates</u> section of this manual.
- **DeviceLock Signing Tool** runs the special tool that allows you to grant users temporary access to requested devices and sign XML files with DeviceLock Service settings. For more information please read the <u>DeviceLock</u> <u>Signing Tool</u> section of this manual.
- About DeviceLock displays the dialog box with information about the DeviceLock version and your licenses.

### **Server Options**

These parameters allow you to tune up the DeviceLock Enterprise Server configuration.



Use the context menu available by a right mouse click or double-click on the **Stream compression** parameter to enable or disable it. By enabling the **Stream compression** parameter, you instruct DeviceLock to compress audit logs and shadow data sending from DeviceLock Services to DeviceLock Enterprise Server. Doing this decreases the size of data transfers and thus reduces the network load.

By enabling the **Unpack ISO images** parameter you can instruct DeviceLock Enterprise Server to extract files from shadowed CD/DVD images. If this parameter is enabled, all files are extracted from CD/DVD images upon delivery to the server and stored in the database separately (one record per file). Otherwise, whole shadowed CD/DVD images are stored in the database.

Use the context menu on other parameters to open dialogs that enable making changes. Alternatively, you can double-click on the parameter to open its dialog box.

All these parameters are described in detail in the <u>Installing DeviceLock Enterprise</u> <u>Server</u> section of this manual.

To run the configuration wizard and review or set all these parameters step by step, use the **Properties** item from the context menu of **Server Options**. The configuration wizard is also described in the <u>Installing DeviceLock Enterprise Server</u> section of this manual.

# Audit Log Viewer (Server)

The audit log viewer allows you to retrieve the audit log stored on DeviceLock Enterprise Server.

DeviceLock Enterprise Server stores audit records received from a remote computer, only if **DeviceLock Log** or **Event & DeviceLock Logs** is selected in the **Audit log type** parameter in <u>Service Options</u> on that computer. Otherwise, audit records are stored in the local Windows event logging subsystem of the remote computer and can be viewed using the <u>service's audit log viewer</u>.



There is not much difference between the service's audit log viewer and the server's audit log viewer, so first read the <u>Audit Log Viewer (Service)</u> section of this manual.

In comparison with the service's audit log viewer, the server's viewer has the following additional columns:

- **Computer** the name of the computer from which audit logs were received.
- **Event** a number identifying the particular event type.
- **Received Date/Time** the date and the time when an event was received by DeviceLock Enterprise Server.

### Audit Log Settings (Server)

To define a maximum log size and what DeviceLock Enterprise Server should do if the audit log becomes full, use **Settings** from the context menu of **Audit Log Viewer**.

Audit Log Settings
Control log size
Maximum log size: 10000 🗘 records
When maximum log size is reached: Overwrite events as needed
Overwrite events older than     7     days
O Do not overwrite events (clear log manually) Restore Defaults
OK Cancel

**Note:** These settings are stored in the database and they are specific to the log but not to DeviceLock Enterprise Server. This means that, if there are several DeviceLock Enterprise Servers using one database, all have the same log settings.

Enable the **Control log size** flag to allow DeviceLock Enterprise Server to control the number of records in the log and delete outdated records (if necessary) to clean up the space for new ones. Otherwise, if the **Control log size** flag is disabled, DeviceLock Enterprise Server uses all available space for the SQL Server's database to store the log.

In the **Maximum log size** parameter you can specify the maximum number of records that this log can contain. Please note that, if there is more than one DeviceLock Enterprise Server using this database, then the actual number of records in the log can be a little larger (by a couple of records) than the specified value.

To specify what DeviceLock Enterprise Server should do when the log is full (when Maximum log size is reached) select one of these options:

- Overwrite events as needed the server will overwrite old events if Maximum log size is reached.
- **Overwrite events older than** specifies that records that are newer than this value will not be overwritten (specified in days).
- **Do not overwrite events (clear log manually)** the server will not overwrite old events if Maximum log size is reached and you will need to clear events manually.

If you wish to reset current settings to the default values, click **Restore Defaults**. Default values are:

- The Maximum log size parameter is set to 10000 records.
- The **Overwrite events older than** option is selected and set to 7 days.

If there is no space for new records in the audit log and there is nothing to delete then DeviceLock Enterprise Server does not remove audit data from remote users' computers. This prevents you from loosing the audit data due to lack of space in the log. When some space becomes available in the log, DeviceLock Enterprise Server moves the remaining audit data from users' computers to this log.

### Audit Log Filter (Server)

You can filter data in <u>Audit Log Viewer</u> so that only records that meet specified conditions are displayed in the list.

To open the **Filter** dialog box, use **Filter** from the context menu of **Audit Log Viewer** or press the appropriate button on the toolbar.

<b>₽</b> S	uccess aut	dik .	<b>₽</b> F	ailure a	udit	
Comput	er:					
Name:						
Source:		Service	6			~
Action		Keylogg	er Detected			~
Informat	tion:					-
User:						_
Process	E				PID:	-
Event If	D:				1	
Gener	rated Date	Time			-	
From	First Ever	nt 🛩	12/17/2010	Y	3:50:42 PM	4 >
To:	Last Ever	nt 💌	12/17/2010	V	3:50:42 PM	<>
Recei	ved Date/	Time				
From	First Ever	nt 🔽	12/17/2010	~	3:50:42 PM	\$
To:	Last Ever	nt 🔽	12/17/2010	~	3:50:42 PM	4.2
To:	Last Ever	nt 🚩	12/17/2010	~	3:50:42 PM	1

There is not much difference between the service's audit log filter and the server's audit log filter, so first read the <u>Audit Log Filter (Service)</u> section of this manual.

In comparison with the service's audit log filter, the server's filter has the following additional fields:

- Computer this text matches a value in the Audit Log Viewer's Computer column. This field is not case-sensitive and you may use wildcards.
   You can enter multiple values separated by a semicolon (;).
- Event ID this number matches a value in the Audit Log Viewer's Event column.

You can enter multiple values separated by a semicolon (;).

Received Date/Time – specifies the time period to filter events based on when they were received by DeviceLock Enterprise Server. From: specifies the earliest date and time from which you want events while To: specifies the latest date and time from which you want events. The possible values of the From: parameter are: First Event, Events On. Select First Event to see events starting with the first event received by DeviceLock Enterprise Server. Select Events On to see events that were received starting with a specific date and time. The possible values of the To: parameter are: Last Event, Events On. Select Last Event to see events ending with the last event

received by DeviceLock Enterprise Server. Select **Events On** to see events that were received ending with a specific date and time.

# Shadow Log Viewer (Server)

The shadow log viewer allows you to retrieve the shadow log stored on DeviceLock Enterprise Server.



There is not much difference between the service's shadow log viewer and the server's shadow log viewer, so first see "<u>Shadow Log Viewer (Service)</u>."

In comparison with the service's shadow log viewer, the server's viewer has only two additional columns:

- **Computer** the name of the computer from which shadow logs were received.
- **Received Date/Time** the date and time when a record was received by DeviceLock Enterprise Server.

Also, unlike the service's shadow log viewer, when you delete a record in the server's viewer, the record's binary data is removed from the database or from the disk (it depends on the <u>Store shadow files in SQL Server</u> flag) but all other information (such as the file name and size, user name, date/time, process and so on) is moved to the special log called <u>Deleted Shadow Data Log</u>.

This Deleted Shadow Data Log is used when you do not need the content of the shadow data anymore and you want to clean up storage (either SQL Server or the disk), but you need to keep information about the data transfer.

### Shadow Log Settings

To define a maximum log size and what DeviceLock Enterprise Server should do if the shadow log becomes full, use **Settings** from the context menu of **Shadow Log Viewer**.

Shadow Log Settings
Control log size
When maximum log size is reached:
Overwrite events as needed     Overwrite events older than     1     days
O Do not overwrite events (clear log manually) Restore Defaults
OK Cancel

For information on these settings, see "Audit Log Settings (Server)."

When DeviceLock Enterprise Server needs to remove some old records from the shadow log because of defined parameters (**Overwrite events as needed** and **Overwrite events older than**), these records are moved to the <u>Deleted Shadow</u> <u>Data Log</u>.

If there is no space for new records in the shadow log and there is nothing to delete then DeviceLock Enterprise Server does not remove shadowed data from remote users' computers. This prevents the loss of shadowed data due to lack of space in the log. When some space becomes available in the log, DeviceLock Enterprise Server moves the remaining shadowed data from users' computers to this log.

It is best to avoid accumulating shadowed data on users' computers. We recommend that you monitor the <u>DeviceLock Enterprise Server's log</u> on a periodic basis, watch for warning messages and adjust log settings appropriately.

#### Shadow Log Filter (Server)

You can filter data in <u>Shadow Log Viewer</u> so that only records that meet specified conditions are displayed in the list.

To open the **Filter** dialog box, use **Filter** from the context menu of **Shadow Log Viewer** or press the appropriate button on the toolbar.

ciude	Exclude				
Shad	ow status				
٧S	uccess		Incomplete	•	Failed
Comput	er: "_dc				
File Nar	ne:				
Source:		_			
Action		-			
loer		_			
Process		-			PID:
Fleri					110.
r no an					
More	Than 💙		1		GB 💌
Gene	rated Date/Time	_		_	
From:	Records On	*	12/ 1/2010	~	11:58:43 AM 🗘
To:	Last Record	~	12/17/2010	V	3:58:43 PM 🗘
Recei	ived Date/Time				
From	First Record	~	12/17/2010	V	3:58:43 PM 💲
To:	Last Record	~	12/17/2010	$\sim$	3:58:43 PM 💲
		_			
			1	La	ad Caus

There is not much difference between the service's shadow log filter and the server's shadow log filter, so first see "<u>Shadow Log Filter (Service)</u>."

In comparison with the service's shadow log filter, the server's filter has the following additional fields:

 Computer – the text that matches a value in the Shadow Log Viewer's Computer column. This field is not case-sensitive and you may use wildcards.

You can enter multiple values separated by a semicolon (;).

 Received Date/Time- specifies the time period to filter records based on when they were received by DeviceLock Enterprise Server. From: specifies the earliest date and time from which you want records while To: specifies the latest date and time from which you want records. The possible values of the From: parameter are: First Record, Records On. Select First Record to see records starting with the first record received by DeviceLock Enterprise Server. Select Records On to see records that were received starting with a specific date and time. The possible values of the To: parameter are: Last Record, Records On. Select Last Record to see records ending with the last record received by DeviceLock Enterprise Server. Select Records On to see records that were received ending with a specific date and time.

### **Deleted Shadow Data Log**

This viewer allows you to retrieve information about deleted shadow log records.

When a record is removed from the log in <u>Shadow Log Viewer</u>, the record's binary data is deleted but all other information (such as the file name and size, user name, date/time, process and so on) is moved to this log.

SeviceLock Management Console				
File Action View Help ← →  €  10  20  10  20  20  20  20  20  20  20  20  20  2	×			
SeviceLock	Status	Computer	Date/Time 💎	Source
Operation of the service (Local, WINXPPROSP3     DeviceLock Enterprise Server (Local, WINX     Operations     Operations	Success	Settings Refresh Filter Clear	/16/2010 7:49	Removable
Deleted Shadow Data Log     Server Log Viewer     Monitoring     Reports     OviceLock Content Security Server		Help		
< >	<			0

This log is used when you do not need the content of the shadow data anymore and you want to clean up the storage (either SQL Server or the disk) but at the same time you need to keep the information about the data transfer.

To define a maximum log size and instruct DeviceLock Enterprise Server regarding what it should do if the deleted shadow data log becomes full, use **Settings** from the context menu available with a right mouse click. This log's settings are similar to the audit log's settings, so see "Audit Log Settings (Server)" for more information.

If there is no space for new records in the deleted shadow data log and there is nothing to remove, then DeviceLock Enterprise Server just drops any new records. To avoid loosing records in this way, we recommend that you monitor <u>DeviceLock</u> <u>Enterprise Server's log</u> on a periodic basis and watch for warning messages there.

To refresh the list, select **Refresh** from the context menu available with a right mouse click or by pressing the appropriate button on the toolbar.

To filter records in this list, select **Filter** from the context menu available with a right mouse click or by pressing the appropriate button on the toolbar. The same filter is used by the Shadow Log Viewer, so see "<u>Shadow Log Filter (Server)</u>" for more information.

To clear all records from this log, select **Clear** from the context menu or press the appropriate button on the toolbar.

# Server Log Viewer

This viewer allows you to retrieve the internal DeviceLock Enterprise Server's log. The server uses this log to write errors, warnings and other important information (such as configuration changes, start/stop events, version, and so on).

File Action View Help ⊨ → 🖻 📧 📴 😰 📧 🔮 ⊽= >	ĸ				
DeviceLock	Туре	Date/Time V	Event	Information	
DeviceLock Service (Local, WINGPROSPS     DeviceLock Enterprise Server (Local, WING     Server Options     Audit Log Viewer     Sarver Log Viewer     Server Log Viewer     Monitoring	Information     Information     Information     Success     Information     Success     Information     Success     Information	12/13/2010 8:34:2 12/13/2010 8:34:2 12/13/2010 8:34:2 12/13/2010 8:34:2 12/13/2010 8:34:2 12/13/2010 8:34:2 12/13/2010 8:34:2	12 13 12 15 22 5 58	Settings Refresh n_ii Filter n_r Clear d's Help set	pc with dynamic n_ip_tcp with er n_np with dyna d successfully. 3/uaw from wins _se Server - 7.0
Reports     GoviceLock Content Security Server	Information	12/12/2010 9:30:2 12/12/2010 9:30:2 12/12/2010 9:30:2	12 15 13	Using protocol nc RPC server initial Using protocol nc	acn_np with dyna zed successfully. acn_ip_tcp with e
	<				>

You may use the information from this log to diagnose problems (if any), to monitor changes in the server's configuration and to see who has cleared logs and when.

The columns of this viewer are defined as follows:

- **Type** the class of an event: **Success**, **Information**, **Warning** or **Error**.
- **Date/Time** the date and the time when an event has occurred.
- **Event** a number identifying the particular event type.
- **Information** event-specific information, such as error/warning descriptions, names and values of changed parameters, and so on.
- Server the name of the server where an event occurred.
- **Record N** the record number.

To refresh the list, select **Refresh** from the context menu available by clicking the right mouse button or by pressing the appropriate button on the toolbar.

To clear all records from this log, select **Clear** from the context menu or press the appropriate button on the toolbar.

After the server's log is cleared, the one event about this clearing action is written into the log (for example, "The Server Log (100 record(s)) was cleared by VM2000AD\Administrator from xpvirt.vm2000ad.com").

#### Server Log Settings

To define a maximum log size and what DeviceLock Enterprise Server should do if the server's log becomes full, use **Settings** from the context menu of **Server Log Viewer**.

Server Log Settings
Control log size
Maximum log size: 1000 🗘 records
When maximum log size is reached:
Overwrite events as needed Overwrite events older than
O Do not overwrite events (clear log manually) Restore Defaults
OK Cancel

For information on these settings, see "Audit Log Settings (Server)."

If there is no space for new records in the server's log and there is nothing to remove, then DeviceLock Enterprise Server just drops any new records.

#### Server Log Filter

You can filter data in the <u>Server Log Viewer</u> so that only records that meet specified conditions are displayed in the list. To open the **Filter** dialog box, use **Filter** from the context menu of **Server Log Viewer** or press the appropriate button on the toolbar.

₹s	uccess nfomation		V Wa V En	erning or	
Inform	ation:				
Server:					
Event I	D:	16			
From:	First Reo	ord 💌	7/19/2006	~	5:14:22 PM 💲
To:	Last Reco	ord 🔽	7/19/2006	~	5:14:22 PM 💲

There are no big differences between defining an Audit Log Filter and a Server Log Filter, so for more information, see "<u>Audit Log Filter (Service)</u>."

When the filter is active you can define its condition by entering values into the following fields:

- Success specifies whether to filter events of the Success class.
- Information specifies whether to filter events of the Information class.
- Warning specifies whether to filter events of the Warning class.
- **Error** specifies whether to filter events of the **Error** class.
- Information the text that matches a value in the Server Log Viewer's Information column. This field is not case-sensitive and you may use wildcards.

You can enter multiple values separated by a semicolon (;).

- **Server** the text that matches a value in the Server Log Viewer's **Server** column. This field is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- **Event ID** the number that matches a value in the Server Log Viewer's **Event** column.

You can enter multiple values separated by a semicolon (;).

- **From** specifies the beginning of the interval of events that you want to filter. Select **First Event** to see events starting with the first event recorded in the log. Select **Events On** to see events that occurred starting with a specific time and date.
- To specifies the end of the range of events that you want to filter. Select
   Last Event to see events ending with the last event recorded in the log.
   Select Events On to see events that occurred ending with a specific time and date.

### Monitoring

This functionality of DeviceLock Enterprise Server allows you to implement real-time monitoring of DeviceLock Services across the network. DeviceLock Enterprise Server can monitor remote computers in real-time, checking DeviceLock Service status (running or not), policy consistency and integrity. The detailed information is written to the special log and can be viewed using the <u>Monitoring Log Viewer</u>.

Also, it is possible to define a master policy that can be automatically applied across selected remote computers in the event that their current policies are suspected to be out-of-date or damaged.

Moreover, you can use this policy recovery feature as an alternative way of deploying settings, permissions, audit and shadowing rules to remote DeviceLock Services
across the network.

# Architecture Overview

All actions (computers monitoring, policy consistency and integrity checking, etc.) are performed by tasks.

On a single DeviceLock Enterprise Server, you can have as many tasks as you wish. The maximum number of tasks on one server is only limited by available memory, CPU and network's bandwidth capacity. Please keep in mind that the server should have enough resources to communicate with at least 10 remote computers simultaneously.

By default, DeviceLock Enterprise Server can execute up to 30 tasks simultaneously. This means that if you have, for example, 40 tasks and all of them run at the same time, the first 30 tasks will run first and each of the remaining 10 tasks will run as soon as others complete.

However, you can change the number of tasks that can be run simultaneously by modifying the registry. To define the new number, open **Regedit** and set the following entry on the computer where DeviceLock Enterprise Server is running:

- Key: HKEY\_LOCAL\_MACHINE\SOFTWARE\SmartLine Vision\DeviceLockEnterpriseServer
- Name: ConcurrentJobs
- Type: **DWORD**
- Value: *number\_of\_threads* where *number\_of\_threads* must be a value between 1 and 1000.

During their execution, tasks write status information to the <u>monitoring log</u> including data about monitored computers and DeviceLock Services. They'll also write possible errors which occurred during the scanning of computers and connecting to DeviceLock Services.

Also, tasks display the status of monitored computers and other useful information at the management console. This allows you to keep an eye on monitored computers in real-time.

I DeviceLock Management Console						
File Action View Help ← →	× 🗈					
Smartline DeviceLock	Computer 🛆	Status	Last Scan Time	Service Uptime		
DeviceLock Service     DeviceLock Enterprise Server	SM2000SERVER	Computer is available Computer is unavailable	12/26/2007 11:19:43 PM 12/26/2007 11:19:37 PM	01:36:24		
Server Options     Audit Log Viewer     Shadow Log Viewer     Server Log Viewer     Monitoring     Monitoring     Critical Machines     Generic Computers	XPVIRT	Settings are corrupted	12/26/2007 11:19:38 PM	00:36:12		
	<			>		

To view the monitored computers that belong to the task, select this task in the console tree.

To refresh the information displayed in the computers list, select **Refresh** from the context menu available by a right mouse click or press the appropriate button on the toolbar.

- **Computer Name** the name of the monitored computer.
- **Status** the status of the monitored computer and DeviceLock Service. The status also affects the small picture (an icon) displayed next to the **Computer Name** parameter. The general rules for interpreting computer icons are:
  - Green computer means that the computer is working and DeviceLock Service is running on it.
  - Red computer means that the computer is not working/not found, or it is working but without DeviceLock Service.
  - Computer with exclamation mark means that something is wrong with the computer or DeviceLock Service.

There can be eight different statuses:

- Computer is available this status means that the monitored computer is working and DeviceLock Service is running on it. Also, if this task verifies policy integrity, then verification happened without any errors. The computer's icon will be "green computer". If this task restores the broken policy, the computer's icon will be "green computer with exclamation mark".
- Computer is unavailable this status means that DeviceLock Enterprise Server is unable to scan the monitored computer. This occurs when a computer is not working or connections are blocked by a firewall, but the computer's name/address can be resolved through DNS. The computer's icon will be "red computer".

- 3. Service is unavailable this status means that DeviceLock Enterprise Server is unable to connect to DeviceLock Service on the monitored computer. This occurs when the computer is working but DeviceLock Service is not running. Also, it could be the result of running DeviceLock Service on a different TCP port than that specified in the task configuration or due to connections being blocked by the firewall. The computer's icon will be "red computer with exclamation mark". For more information on connection issues, see the description of the <u>Service connection settings</u> parameter.
- 4. Settings are corrupted this status means that the monitored computer is working and DeviceLock Service is running on it but the policy verification process has failed. This happens when the master policy is assigned to a task and it differs from the monitored DeviceLock Service policy. The computer's icon will be "green computer with exclamation mark".
- 5. Unresolved computer address this status means that DeviceLock Enterprise Server is unable to resolve the name/address of the computer. This happens when an invalid computer name that does not exist in DNS is specified. Also, it could happen because there is no DNS server. In this case the Unresolved computer address status should be treated as Computer is unavailable. The computer's icon will be "red computer with exclamation mark".
- 6. **Unsupported service version** this status means that DeviceLock Enterprise Server is trying to download a policy (service settings) from DeviceLock Service version 6.2 and lower. The policy verification is supported only for version 6.2.1 and later. The computer's icon will be "green computer with exclamation mark".
- 7. Access is denied this status means that DeviceLock Enterprise Server is unable to connect to DeviceLock Service due to lack of privileges. It happens when the account under which the DeviceLock Enterprise Server service starts has no rights to connect to DeviceLock Service. The computer's icon will be "green computer with exclamation mark". For more information on how to resolve this issue, see the description of the <u>Service connection settings</u> parameter.
- 8. No License this status means that DeviceLock Enterprise Server is unable to monitor the computer running DeviceLock Service due to an insufficient number of licenses. DeviceLock Enterprise Server handles as many DeviceLock Service instances as there are licenses loaded into DeviceLock Enterprise Server. For more information, see "License information" in "Installing DeviceLock Enterprise Server". The computer's icon will be "green computer with exclamation mark".

Also, the same status messages (except **Computer is available**) are written to the <u>monitoring log</u> so you can overview the situation with monitored computers later.

- Last Scan Time the date and time of the last scan attempt. This scan attempt can be either successful or not.
- Last Successful Scan Time the date and time of the last successful scan attempt.
- Service Uptime shows how long DeviceLock Service has been working on the monitored computer.

- **Computer Uptime** shows how long the monitored computer has been working. By comparing the computer's uptime with the service's uptime (see above) you can always see whether or not DeviceLock Service was stopped during the current computer's session.
- **Service Version** the version of DeviceLock Service. Last five digits indicate the build number.

# Monitoring Algorithm

The algorithm used in the monitoring process is simple but effective:

- 1. First of all DeviceLock Enterprise Server tries to scan the monitored computer to determine whether or not it is working. If the scan succeeds then the computer receives the **available** status and computer monitoring continues. Otherwise, it receives the **unavailable** status and computer monitoring stops (the record is written to the monitoring log).
- Then DeviceLock Enterprise Server tries to connect to DeviceLock Service. If the connection succeeds then DeviceLock Service receives the **available** status and computer monitoring continues. Otherwise, it receives the **unavailable** status and computer monitoring stops (the record is written to the monitoring log).
- 3. If this task should verify DeviceLock Service policy integrity then computer monitoring continues. Otherwise, computer monitoring stops (nothing logged).
- 4. DeviceLock Enterprise Server downloads the policy from DeviceLock Service and compares it with the master policy assigned to this task. If no difference is found computer monitoring stops (nothing logged). If there is a difference between the two policies then computer monitoring continues (the record is written to the monitoring log).
- 5. If this task should restore the broken policy, then DeviceLock Enterprise Server writes the master policy to DeviceLock Service and computer monitoring stops (the record is written to the monitoring log). Otherwise, computer monitoring just stops (nothing logged).

If some error occurs at any step described above, then the record about that will be written to the monitoring log. If this error is not critical, computer monitoring may continue. If it is a critical error then computer monitoring stops.

Also, some very critical errors (such as "no memory") can halt execution of the whole task.

#### Create / Modify Task

Each task contains its own set of computers, actions and configuration parameters.



To create a new task, use **Create Task** from the context menu of the **Monitoring** item. To edit an existing task, select this task in the console tree and use **Edit Task** from the context menu. If you wish to delete the task permanently, select this task in the console tree and use **Delete Task** from the context menu.

🔯 Edit Task	? 🛛
Name:	Critical Machines
Active	
Computers:	Static list 💌 Edit
Network discove	ery methods:
Ping sweep	Advanced settings
NetBIOS que	rries
TCP discover	ry (ports):
Service connect	ion settings:
<ul> <li>Dynamic por</li> </ul>	ts
O Fixed TCP po	ort:
Verify Servic	e Settings:
Service Settings	file: Configured (Service Settings - [26] Save
Restore Ser	vice Settings
Scanning interv	al: 5 📚 sec
Number of scan	ning threads:
	OK Cancel

**Name** – the name of the task used to identify this task in the tasks list and in the monitoring log.

**Active** – if selected, allows DeviceLock Enterprise Server to execute this task. Clear this check box if you wish to disable the task but do not want to delete it permanently.

**Computers** – the type of the computers list used to define what computers will be monitored by this task.

Click the **Edit** button to configure the list selected in **Computers**.

Two computer list types are supported:

1. **Static list** – all of the computers are specified in the list by their names or IP addresses. Since this list is static, even if some computer no longer exists in the network, it will be monitored (and the error logged) until its record is deleted from the list manually.

🛃 Edit static list		? 🔀
Select computer(s) Computers Image: Computers	< WM2000SERVER WMNT4SP6 XPVIRT >>	
	ОК	Cancel

Computers that will be monitored should be specified in the right list. You have to select needed computers in the left list and then move them to the right list by clicking the > button.

If you need to exclude some computers from the monitoring process, select them in the right list and then click the < button.

By using >> and << buttons, you can add and remove all available computers at the same time (no need to select computers in the list).

There are several flexible ways to choose network computers from the left list:

- **Computers** you browse the network tree and select computers.
- From File you load a predefined list of computers from the external text file and then select the computers. To open an external file, click

the ... button. A text file must contain each computer's name or IP address on separate lines and can be either Unicode or non-Unicode.

- **Manual** you type computer names manually to select the computers. Each computer's name or IP address must be typed on a separate line.
- 2. Dynamic list instead of computer names or IP addresses, the dynamic list contains a path to the container (for example, an organizational unit) in the directory service tree (such as Active Directory, Novell eDirectory, OpenLDAP and so on). Each time the task is executing, DeviceLock Enterprise Server retrieves all the computers that currently exist in this container. Hence, if some computer was removed from the directory tree or moved to another container it will not be monitored anymore. And vice versa, if there is some new computer that did not exist in the container at the time the task was created/modified, but was added to this container later, it will be retrieved and monitored at the time of executing the task.

**Note:** If DeviceLock Enterprise Server is running on Windows NT4, then using Dynamic list requires that Active Directory Extension be installed. You can download it from:

http://www.microsoft.com/downloads/details.aspx?displaylang=en&FamilyID=7c219dc c-ec00-4c98-ba61-fd98467952a8

🛃 Edit dynamic list 🛛 💽 🔀
Select path from the Active Directory tree
Active Directory
Builtin       Computers      Computers      Consin Controllers       Consin Controllers       Consin Controllers       Consin Controllers      Users
Select Synchronization
LDAP://CN=Computers,DC=vm2000ad,DC=com
Traverse subcontainers when enumerating computers
OK Cancel

A path to the container from which computers will be retrieved at the time of executing the task, should be specified in the **Path** parameter. You must use the LDAP string representation for distinguished names.

You may browse the directory tree and choose the needed container by clicking the **Select** button. In this case a path to this container will be specified in the **Path** parameter automatically.

Select the **Traverse subcontainers when enumerating computers** check box to allow DeviceLock Enterprise Server to retrieve computers from all the nested containers located inside the selected container. Otherwise, if this check box is unselected all nested containers are ignored, and only computers located directly in the selected container are retrieved at the time of executing the task.

There are two modes to work with the directory service:

 Active Directory – You browse the Active Directory tree and select the needed container.

While the Active Directory tree can also be displayed by choosing the **LDAP** option (see below), the Active Directory mode results in greater efficiency between the directory service and DeviceLock Enterprise Server service and thus resource savings.

If you need to supply alternative credentials to access Active Directory, click the ... button to open the **Credentials** dialog box and specify the needed user account and its corresponding password.

**Note:** If no alternative credentials are specified when accessing Active Directory, DeviceLock Enterprise Server uses the credentials of the account under which its service started. For more information, see the description of the <u>Log on as</u> parameter.

Select the **Synchonization** check box to allow DeviceLock Enterprise Server to use the internal synchronization mechanisms provided by Active Directory. This will dramatically reduce the load on the domain controller and speed up the process of retrieving computers at the time of task execution.

**Note:** Administrative access to Active Directory is required to use the synchronization function.

 LDAP – You browse the LDAP (Lightweight Directory Access Protocol) tree and select the needed container.

To configure a connection to the LDAP server, click the ... button and open the **LDAP Settings** dialog box.

LDAP Setting	s	? 🔀
Host: Port: Base DN: User DN:	VM2000SERVER 389 CN=Configuration,DC=vm2000ad,DC=com	 Eetch
Pagsword:		
		ancel

**Host** – the name or the IP address of the LDAP server to connect to. **Port** – the TCP port on which the LDAP server accepts connections. The default port is 389.

**Base DN** – the starting point for you to browse the directory tree. You must use the LDAP string representation for distinguished names (for

example, cn=qa,o=SMARTLINE,c=US). Leave the **Base DN** box blank to start browsing from the root.

By clicking the **Fetch** button, you can get all the published naming contexts.

**User DN** – the distinguished name (DN) of the directory user that allows connection to the directory. You must use the LDAP string representation for distinguished names (for example, cn=admin,o=SMARTLINE,c=US).

**Note:** If no user is specified when accessing the LDAP server, DeviceLock Enterprise Server uses the credentials of the account under which its service started. For more information, see the description of the <u>Log on as</u> parameter.

**Password** – the user's password.

**Network discovery methods** – types of network scanning that will be used to determine the status (**available** or **unavailable**) of monitored computers.

Upon executing the task, DeviceLock Enterprise Server uses all selected discovery methods in their given order until the status **available** is returned for the target computer. If none of the selected methods returns the **available** status, then the target computer receives the **unavailable** status.

Three types of the network scan are supported:

- 1. **Ping sweep** DeviceLock Enterprise Server sends a regular ICMP ping to the target computer and then waits for its reply.
- NetBIOS queries if the Client for Microsoft Networks is installed on the target computer, then this computer will answer the NetBIOS type query sent by DeviceLock Enterprise Server.
- TCP discovery (ports) DeviceLock Enterprise Server checks for a particular open TCP port on the target computer. Using the comma (,) or semicolon (;) as a separator, you can specify several ports so they will be checked one by one in their given order.

**Note:** A firewall running on a target computer can block the sending of some or all network packets so such a computer will be detected as unavailable even if it is switched on and working.

To define additional parameters for discovery methods, click the **Advanced settings** button and open the **Network Discovery Settings** dialog box.

Network Discovery Settings 💦 🔀
Number of retries: 0 🛟 Reply timeout: 2 🛟 sec
OK Cancel

**Number of retries** – the number of times that DeviceLock Enterprise Server will perform each type of scan when it returns the **unavailable** status. 0 means that no retries will be performed for that scan type after the first failed attempt.

**Reply timeout** – the time in seconds DeviceLock Enterprise Server will actually wait for a response from the target computer for each type of scan. If DeviceLock Enterprise Server is running on a slow or busy network you may need to increase this timeout.

**Service connection settings** – these options define how DeviceLock Enterprise Server should connect to DeviceLock Services on the monitored computers to obtain service version, settings, etc. If the correct connection settings are not specified, DeviceLock Enterprise Server will not be able to connect to monitored services and their computers will not receive the **available** status.

DeviceLock Service can be configured to use either a fixed port or dynamic ports during the installation process. For more information on this, see "<u>Unattended</u> <u>Installation</u>" and "<u>Remote Installation via DeviceLock Enterprise Manager</u>."

There are two connection options:

- **Dynamic ports** to instruct DeviceLock Enterprise Server to use dynamic ports for communication with DeviceLock Service, select this option.
- Fixed TCP port if DeviceLock Service is configured to accept connections on a fixed port, then you should select this option and specify that port number.

**Note:** In order to successfully connect to monitored DeviceLock Services and obtain needed information from them, DeviceLock Enterprise Server must have at least Read-only access rights to these services. If this task also needs to write some settings to monitored DeviceLock Services, then DeviceLock Enterprise Server requires Full access rights to these services.

To connect to monitored DeviceLock Services, DeviceLock Enterprise Server uses the credentials of the account under which its service started. It can also use DeviceLock Certificate authentication, if a private key is specified. For more information, see the description of parameters Log on as and Certificate Name.

**Verify Service Settings** – select this check box if you want to verify policy integrity for DeviceLock Services running on monitored computers.

• Service Settings file – to assign the master policy to the task, you should load the XML file with service settings (the master policy file). This master policy file can be created using DeviceLock Management Console, DeviceLock Group Policy Manager and/or DeviceLock Service Settings Editor.

During the policy verification process, DeviceLock Enterprise Server downloads the policy from each monitored DeviceLock Service and compares it with the master policy assigned to this task. All unconfigured parameters (those which have the **Not Configured** state) in the master policy are ignored during the policy verification process. Using this feature you can monitor the integrity of only the most important parameters and allow other parameters to be changed without being reported to the monitoring log.

To load the master policy file, click the ... button. Since the signature is not validated at this step, it can be either a signed or non-signed file. However, if you load the signed file then its name will be displayed in the **Service Settings file** box in round brackets.

If you are modifying the task and the master policy is already assigned, you can export it to an external XML file by clicking the **Save** button.

Restore Service Settings – if selected, DeviceLock Enterprise Server will
overwrite the current policy of a monitored DeviceLock Service for which the
policy verification process failed with the master policy assigned to this task.
Using this feature you can not only passively monitor the integrity of specific
parameters but also restore them in case they were changed.

**Scanning interval** – the time in seconds that should pass after a task completes and before DeviceLock Enterprise Server will start executing the same task again.

**Number of scanning threads** – the maximum number of threads that can be used by this task simultaneously. You can increase this number to parallelize the process of computer scanning. However, a larger number of threads requires more hardware resources (especially RAM and network bandwidth) for DeviceLock Enterprise Server.

# Monitoring Log Viewer

This viewer allows you to retrieve the monitoring log. The monitoring log is used by tasks to write information about monitored computers and DeviceLock Services.

💐 DeviceLock Management Console 📃 🗖 🔀						×	
File Action View Help ← → 💽 🖬 🗒 😭	⊽= 🗙						
Smartline DeviceLock	Туре	Date/Time V		Event	Task Name	Computer Name	^
DeviceLock Service	Information	12/26/2007 10	:47:24 PM	4	Critical Machines		-
E DeviceLock Enterprise Server	Success	12/26/2007 10	:47:24 PM	10	Critical Machines	VMNT4SP6	
Audit Lee Viewer	Warning	12/26/2007 10	:47:22 PM	17	Critical Machines	VMINT4SP6	
Audit Log Viewer	Success	12/26/2007 10	:47:22 PM	10	<b>Critical Machines</b>	VM2000SERVER	
Server Log Viewer	🔥 Warning	12/26/2007 10	:47:21 PM	17	<b>Critical Machines</b>	VM2000SERVER	
	Information	12/26/2007 10	:47:21 PM	з	<b>Critical Machines</b>		
A Monitoring Log Viewer	Information	12/26/2007 10	:47:16 PM	4	<b>Critical Machines</b>		
Critical Machines	🔥 Warning	12/26/2007 10	:47:16 PM	17	<b>Critical Machines</b>	VMINT4SP6	
Generic Computers	🔥 Warning	12/26/2007 10	:47:15 PM	17	<b>Critical Machines</b>	VM2000SERVER	
	Information	12/26/2007 10	:47:15 PM	3	<b>Critical Machines</b>		v
	<b>(</b>	ш)				>	Ē
Total: 7914							

The columns of this viewer are defined as follows:

- Type the class of an event: Success, Information, Warning or Error.
- **Date/Time** the date and the time when an event has occurred.
- **Event** a number identifying the particular event type.
- **Task Name** the name of the task responsible for this event. Can be empty if an event does not link to any task.
- **Computer Name** the name of the computer belonging to the task that is responsible for this event. Can be empty if an event does not link to the computer.
- **Information** event-specific information, such as status, error, warning, and so on.
- Server the name of the server where an event occurred.
- **Record N** the record number.

To refresh the list, use **Refresh** from the context menu available by clicking the right mouse button or by pressing the appropriate button on the toolbar.

To clear all records from this log, use **Clear** from the context menu or press the appropriate button on the toolbar.

# Monitoring Log Settings

To define a maximum log size and instruct DeviceLock Enterprise Server in the event the monitoring log becomes full, use **Settings** from the context menu of the **Monitoring Log Viewer**.

Monitoring Log Settings
Control log size Maximum log size: 10000 records When maximum log size is reached: Overwrite events as needed Overwrite events older than T to days Do not overwrite events Pestore Defaults
(clear log manually) (Kostol o Do daks) OK Cancel

For information on these settings, see <u>Audit Log Settings (Server</u>).

#### **Monitoring Log Filter**

You can filter data in the <u>Monitoring Log Viewer</u> so that only records that meet specified conditions are displayed in the list.

To open the **Filter** dialog box, use **Filter** from the context menu of the **Monitoring Log Viewer** or press the appropriate button on the toolbar.

nclude	Exclude				
Even S	t types iuccess nfomation		□ W V Er	arning ror	
Compu	ter name:	xpvirt			
Task n	ame:				
Informa	tion:				
Server:					
Eventl	D:				
From:	First Red	ord 💌	12/26/2007	$\sim$	11:24:53 PM 👙
Τα	Last Re	cord 🔽	12/26/2007	~	11:24:53 PM 👙
🗹 Ena	ble filter		(	Load	Save

There is no significant difference between defining an Audit Log Filter and a Monitoring Log Filter, so for more information see "<u>Audit Log Filter (Service)</u>."

When the filter is active you can define its condition by entering values into the following fields:

- Success specifies whether to filter events of the Success class.
- Information specifies whether to filter events of the Information class.
- Warning specifies whether to filter events of the Warning class.
- Error specifies whether to filter events of the Error class.
- **Computer Name** the text that matches a value in the Monitoring Log Viewer's **Computer Name** column. This field is not case-sensitive and you may use wildcards.

You can enter multiple values separated by a semicolon (;).

 Task Name – the text that matches a value in the Monitoring Log Viewer's Task Name column. This field is not case-sensitive and you may use wildcards.

You can enter multiple values separated by a semicolon (;).

 Information – the text that matches a value in the Monitoring Log Viewer's Information column. This field is not case-sensitive and you may use wildcards.

You can enter multiple values separated by a semicolon (;).

- **Server** the text that matches a value in the Monitoring Log Viewer's **Server** column. This field is not case-sensitive and you may use wildcards. *You can enter multiple values separated by a semicolon (;).*
- **Event ID** the number that matches a value in the Monitoring Log Viewer's **Event** column.

You can enter multiple values separated by a semicolon (;).

- **From** specifies the beginning of the interval of events that you want to filter. Select **First Event** to see events starting with the first event recorded in the log. Select **Events On** to see events that occurred starting with a specific time and date.
- To specifies the end of the range of events that you want to filter. Select
   Last Event to see events ending with the last event recorded in the log.
   Select Events On to see events that occurred ending with a specific time and date.

# Managing and Using DeviceLock Content Security Server

# Navigating DeviceLock Content Security Server

Before addressing the functionality of DeviceLock Content Security Server, you need to examine how to perform basic navigation.

Use the **DeviceLock Content Security Server** node in DeviceLock Management Console to configure and use DeviceLock Content Security Server.

SeviceLock Management Console (TA	NYADC\administrator) 🛛 🔲 🔀
Eile Action View Help	
	🗄 😫 💡
I DeviceLock	Name
DeviceLock Service     DeviceLock Enterprise Server     DeviceLock Content Security Server     Server Options     Search Server Options     Search Server     Search Server     Search Page     Current Activity	Server Options
	Local Computer

Right-click the **DeviceLock Content Security Server** node to display the following commands:

 Connect – connects to the computer running DeviceLock Content Security Server. For more information, see <u>"Connecting to Computers</u>."

When you connect to a computer where an old version of DeviceLock Content Security Server is installed, you may receive the following message:

DeviceL	ock - SearchServerConnect error! (7049) 🛛 🛛 🔀
8	The product version on the client and server machines does not match.
	OK

In this case you need to install the new version of DeviceLock Content Security Server on this computer. For information on how to install DeviceLock Content Security Server, see "<u>Installing DeviceLock Content</u> <u>Security Server</u>."

- **Reconnect** connects to the currently connected computer once again.
- **Connect to Last Used Server at Startup** click this command to instruct DeviceLock Management Console to automatically connect to the last used server each time the console starts up.
- Certificate Generation Tool runs the special tool that allows you to generate DeviceLock Certificates. For more information, see "Generating DeviceLock Certificates."
- DeviceLock Signing Tool runs the special tool that allows you to grant users temporary access to requested devices and sign XML files with DeviceLock Service settings. For more information, see "<u>DeviceLock Signing</u> <u>Tool</u>."
- **About DeviceLock** displays the dialog box with information about the DeviceLock version and your licenses.

Expand the **DeviceLock Content Security Server** node to display the following sub-nodes:

• The **Server Options** node. Use this node to configure DeviceLock Content Security Server and Search Server.

The following list describes the general settings that you can configure for DeviceLock Content Security Sever:

- Server Administrators Use this setting to specify members of the Server Administrators group and their associated access rights.
- **DeviceLock certificate** Use this setting to install or remove DeviceLock Certificate.
- **Service startup account** Use this setting to specify the startup account information, such as the account name and the password, for the server service.
- **TCP port** Use this setting to specify the TCP port that the server uses to connect to DeviceLock Management Console.

The following list describes the full-text search related settings that you can configure for Search Server:

- DeviceLock Enterprise Server(s) Use this setting to specify DeviceLock Enterprise Server(s) whose data will be indexed for fulltext search.
- **Index directory** Use this setting to specify the location of the full-text index.
- **Indexing interval** Use this setting to specify the time interval, in minutes, between the end of one indexing process and the start of the next indexing process.
- **Merge Interval** Use this setting to specify the time interval, in minutes, at which to perform merge operations.
- **Extract text from binary** Use this setting to allow or disallow the index to include textual information from binary data.
- Search Server License(s) Use this setting to install the required number of Search Server licenses.
- The **Search Server** node. Use this node to perform a search operation and monitor the current indexing activity.

# Configuring General Settings for DeviceLock Content Security Server

There are two types of configuration settings for DeviceLock Content Security Server:

- **General settings for DeviceLock Content Security Server.** These settings affect your whole DeviceLock Content Security Server deployment.
- **Full-text search settings for Search Server.** These settings are related to full-text search and affect only the Search Server component of DeviceLock

Content Security Server. For more information, see "<u>Configuring Full-Text</u> <u>Search Settings for Search Server</u>."

You can configure general server settings during the initial installation of DeviceLock Content Security Server, or you can use DeviceLock Management Console to configure and/or modify them after the server has been installed and is functioning.

**Note:** You must be a member of the Server Administrators group and have sufficient rights to manage and use DeviceLock Content Security Server.

Before you can use DeviceLock Management Console, you must connect it to the computer on which DeviceLock Content Security Server is installed and running. To do so, in the console tree, right-click **DeviceLock Content Security Server**, and then click **Connect**. For more information, see "Connecting to Computers."

With DeviceLock Management Console, you can perform the following configuration tasks:

- Configure which users have access to DeviceLock Content Security Server.
- Change the startup account information, such as the account name or the password, for the DeviceLock Content Security Server service.
- Install or remove DeviceLock Certificate used to authenticate communications between DeviceLock Content Security Server and DeviceLock Enterprise Server.
- Change the TCP port that DeviceLock Content Security Server uses to connect to DeviceLock Management Console.

You can perform these tasks individually or collectively.

To perform the tasks collectively, you can use the DeviceLock Content Security Server wizard. This is the wizard that starts automatically when you install or upgrade DeviceLock Content Security Server.

#### To perform configuration tasks collectively

- 1. In the console tree, expand **DeviceLock Content Security Server**.
- 2. Under **DeviceLock Content Security Server**, right-click **Server Options**, and then click **Properties**.

The first page of the wizard appears.

3. Move through the wizard. After completing each page, move to the following one by clicking **Next**, or move to the preceding one by clicking **Back**. On the final page, click **Finish** to complete the wizard.

*For detailed information on how to configure DeviceLock Content Security Server using the configuration wizard, see* "*Installing DeviceLock Content Security Server.*"

Below are step-by-step instructions explaining how to perform individual configuration tasks using DeviceLock Management Console.

#### Task: Configure which users have access to DeviceLock Content Security Server

You can select users you want to have access to your DeviceLock Content Security Server. This restricts outsiders from accessing or damaging the server.

#### To configure which users have access to the server

- 1. In the console tree, expand **DeviceLock Content Security Server**.
- 2. Under **DeviceLock Content Security Server**, do one of the following:
  - Select Server Options. In the details pane, double-click Server Administrators or right-click Server Administrators and then click Properties.

When you select Server Options in the console tree, they are displayed in the details pane.

- OR -

• Expand Server Options. Under Server Options, right-click Server Administrators and then click Properties.

The DeviceLock Content Security Server dialog box appears.

TO DO THIS	FOLLOW THESE STEPS
To enable default security	• Select the <b>Enable Default Security</b> check box. If default security is enabled, members of the local Administrators group will have full access to DeviceLock Content Security Server.
To restrict	1. Clear the Enable Default Security check box.
access to the server to specific users	<ol> <li>Under Users, click Add to add the specific users to whom you want to allow access to DeviceLock Content Security Server.</li> </ol>
	The Select Users or Groups dialog box appears.
	<ol> <li>In the Select Users or Groups dialog box, in the Enter the object names to select box, type the name of the user or group, and then click OK.</li> </ol>
	<ul> <li>The users and groups you selected are added to the Server Administrators group and are displayed under Users in the DeviceLock Content Security Server dialog box. Server Administrators are users or groups that are authorized to perform tasks related to configuring and using DeviceLock Content Security Server. By default, members of the Server Administrator group have full access rights to the server. To change their access rights, under Users, select the user or group and then click any option in the access rights list. The available options are:</li> <li>Full Access – enables full access to DeviceLock Content Security Server. Users can install/uninstall DeviceLock Content Security Server, connect to it using DeviceLock Management Console, change its settings and run search</li> </ul>

3. In the **DeviceLock Content Security Server** dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS
	queries. <b>Change</b> - enables change access to DeviceLock Content Security Server. Users can install/uninstall DeviceLock Content Security Server, connect to it using DeviceLock Management Console, change its settings, and run search queries; but they cannot add and remove users to and from the Server Administrators group or change access rights granted to Server Administrators. <b>Read-only</b> - enables read-only access to DeviceLock Content Security Server. Users can connect to DeviceLock Content Security Server using DeviceLock Management Console, run search queries and view settings; but they cannot modify any settings or create a new index for Search Server.
	<b>Note:</b> We strongly recommend that members of the Servers Administrators group have local administrator privileges.
	To remove a user or group from the Server Administrators group, under <b>Users</b> , select the user or group, and then click <b>Delete</b> . You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

#### Task: Change the service startup account or password

Over time, you might need to change the account that you specified as the service startup account for DeviceLock Content Security Server during the installation process. You can also change the password of the service startup account.

#### To change the service startup account or password

- 1. In the console tree, expand **DeviceLock Content Security Server**.
- 2. Under DeviceLock Content Security Server, select Server Options.

When you select Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **Service startup account** or right-click **Service startup account** and then click **Properties.** 

The DeviceLock Content Security Server dialog box appears.

4. In the **DeviceLock Content Security Server** dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS		
To change the service startup account	<ol> <li>In the Log on as area, click Browse. The Select User dialog box appears.</li> <li>In the Select User dialog box, in the Enter the object</li> </ol>		

TO DO THIS	FOLLOW THESE STEPS
	name to select box, type the name of the user, and then click <b>OK</b> .
	The user that you selected is displayed in the This account box in the DeviceLock Content Security Server dialog box.
	We recommend that you use an account that has administrative privileges on all computers running DeviceLock Enterprise Server. In a domain environment, we recommend that you use an account that is a member of the Domain Admins group. Otherwise, you will need to use DeviceLock Certificate authentication.
To change the service account	<ol> <li>In the Log on as area, type a new password in the Password box.</li> </ol>
password	<ol> <li>Re-type your new password in the Confirm password box.</li> </ol>
To assign the Local System account to the server service	<ul> <li>In the Log on as area, click Local System account.</li> <li>If the service uses this account, it cannot access</li> <li>DeviceLock Enterprise Server running on a remote</li> <li>computer and must use the DeviceLock Certificate for</li> <li>authentication on it.</li> </ul>

#### Task: Install or remove DeviceLock Certificate used to authenticate communications between DeviceLock Content Security Server and DeviceLock Enterprise Server

There can be situations when the user account under which DeviceLock Content Security Server is running cannot access remote DeviceLock Enterprise Server. In these situations, you can use DeviceLock Certificate authentication. To do so, install the same private key of DeviceLock Certificate on DeviceLock Content Security Server and DeviceLock Enterprise Server. For detailed information on DeviceLock Certificates, see "DeviceLock Certificates."

# To install or remove DeviceLock Certificate on DeviceLock Content Security Server

- 1. In the console tree, expand **DeviceLock Content Security Server**.
- 2. Under DeviceLock Content Security Server, select Server Options.

When you select Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **DeviceLock certificate** or right-click **DeviceLock certificate** and then click **Properties.** 

The DeviceLock Content Security Server dialog box appears.

4. In the **DeviceLock Content Security Server** dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS
To install the private key of DeviceLock Certificate	<ol> <li>Next to the Certificate Name box, click the ellipsis button is to open the Select the DeviceLock Certificate file dialog box and browse for the file to use.</li> </ol>
	<ol> <li>In the Select the DeviceLock Certificate file dialog box, in the Look in list, click the location that contains the certificate file.</li> </ol>
	<ol><li>In the folder list, locate and open the folder that contains the certificate file.</li></ol>
	4. Click the file, and then click <b>Open</b> .
	The certificate name now appears in the Certificate Name box of the DeviceLock Content Security Server dialog box.
To remove the private key of DeviceLock Certificate	<ul> <li>Next to the Certificate Name box, click Remove.</li> </ul>

# Task: Change the TCP port that is used to connect to DeviceLock Management Console

Over time, you might need to change the TCP port that DeviceLock Content Security Server uses to connect to DeviceLock Management Console.

# To change the TCP port that is used to connect to DeviceLock Management Console

- 1. In the console tree, expand **DeviceLock Content Security Server**.
- 2. Under DeviceLock Content Security Server, select Server Options.

When you select Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **TCP port** or right-click **TCP port** and then click **Properties.** 

The DeviceLock Content Security Server dialog box appears.

- 4. In the **DeviceLock Content Security Server** dialog box, in the **Connection Settings** area, do one of the following:
  - Click Dynamic ports to configure DeviceLock Content Security Server to use a dynamic port.
     - OR -
  - Click **Fixed TCP port** to configure DeviceLock Content Security Server to use a static port. Next, type the port number in the **Fixed TCP port** box.

*By default, DeviceLock Content Security Server communicates over TCP port* 9134.

# **Configuring Full-Text Search Settings for Search Server**

Full-text search settings are related to full-text search and apply only to the Search Server component of DeviceLock Content Security Server.

During the installation of DeviceLock Content Security Server, you can only install the Search Server licenses. Use DeviceLock Management Console to define the full set of Search Server configuration options.

With DeviceLock Management Console, you can perform the following configuration tasks:

- Install the required number of Search Server licenses.
- Specify DeviceLock Enterprise Server(s) whose data will be indexed for fulltext search.
- Specify the location of the full-text index.
- Allow or disallow the index to include textual information from binary data.
- Configure the full-text indexing schedule.
- Configure a schedule for merge operations.
- Rebuild the full-text index immediately.
- Update the existing index immediately.
- Monitor and refresh the status of the current indexing activity.

# Task: Install the required number of Search Server licenses

There is a special Search Server license which you must purchase for DeviceLock Content Security Server. You can use the same license on an unlimited number of computers running DeviceLock Content Security Server.

The Search Server licensing model is based on the number of log entries to be indexed for full-text search. Each license allows Search Server to index 1,000 entries from the shadow logs (Shadow Log and Deleted Shadow Log), and 5,000 entries from every other log (Audit Log, Server Log, and Monitoring Log).

Depending on the actual number of log entries on your DeviceLock Enterprise Servers, you can purchase as many licenses as required. If you use several licenses for Search Server, it can index as many log entries as the combined licenses allow. The trial period for DeviceLock Content Security Server is 30 days. During the trial period, Search Server can index 2,000 entries from the shadow logs and 10,000 entries from every other log. You can always purchase and install additional Search Server licenses.

#### To install Search Server licenses

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Server Options**.
- 2. Under Server Options, select Search Server Options.

When you select Search Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **Search Server License(s)** or right-click **Search Server License(s)** and then click **Properties.** 

The DeviceLock Content Security Server dialog box appears.

- 4. In the **DeviceLock Content Security Server** dialog box, click **Load License(s)** to browse for the license file.
- 5. In the **Select the DeviceLock license file** dialog box, in the **Look in** list, click the location that contains the license file.
- 6. In the folder list, locate and open the folder that contains the license file.
- 7. Click the file, and then click **Open**.

Information about installed license files is displayed in the License information area of the DeviceLock Content Security Server dialog box.

You can install as many licenses as required to suit your organization's needs. To do this, add them one by one.

8. Click **OK**.

#### Task: Specify DeviceLock Enterprise Server(s) whose data will be indexed for fulltext search

To start the process of creating the full-text index, you must specify DeviceLock Enterprise Server(s) whose data will be indexed. Search Server starts the indexing process automatically as soon as you specify DeviceLock Enterprise Server(s).

#### To specify DeviceLock Enterprise Server(s)

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Server Options**.
- 2. Under Server Options, select Search Server Options.

When you select Search Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **DeviceLock Enterprise Server(s)** or rightclick **DeviceLock Enterprise Server(s)** and then click **Properties**.

The DeviceLock Enterprise Server(s) dialog box appears.

🖲 DeviceLock Enterprise Server(s)	? 🛛
Computer Name: Local Computer	
DeviceLock Enterprise Server(s):	
1	Remove
ОК	Cancel

4. In the **DeviceLock Enterprise Server(s)** dialog box, type the IP address or the name of the computer that is running DeviceLock Enterprise Server.

*Multiple computer names or IP addresses must be separated by a semicolon (;).* 

**Note:** Make sure that DeviceLock Enterprise Server is properly installed and accessible to DeviceLock Content Security Server, otherwise its data will not be indexed by Search Server.

To remove computer names or IP addresses, click **Remove**.

5. Click **OK**.

#### Task: Specify the location of the full-text index

You can specify where the full-text index will reside. If you do not specify a location, the full-text index is created in the default directory

**%ProgramFiles%\DeviceLock Content Security Server\Index**. Search Server starts the indexing process automatically each time you specify a different location.

#### To specify the index location

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Server Options**.
- 2. Under Server Options, select Search Server Options.

When you select Search Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **Index directory** or right-click **Index directory** and then click **Properties**.

The Index Directory dialog box appears.

🚰 Index Directory	? 🛛
Computer Name: Local Comp	uter
C:\Program Files\DeviceLock	Content Security Server\Index
Greate New Index	
	OK Cancel

4. In the **Index Directory** dialog box, in the **Index Directory** box, type the path that you want to use as your default index location.

If you want to immediately create a new index, select the **Create New Index** check box.

If the index already exists at the specified location and you choose to create a new index, the following message box is displayed:

DeviceL	ock 🛛 🔀
2	Do you want to create the new index and overwrite the existing one (Yes - Overwrite, No - Append)?
	Yes No Cancel

In the message box, click **Yes** to completely rebuild the full-text index immediately. Click **No** to update the existing full-text index with changes immediately.

5. Click **OK**.

Task: Allow or disallow the index to include textual information from binary data

You can allow or disallow the index to include textual information from binary data.

To enable or disable the extraction of text from binary data

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Server Options**.
- 2. Under Server Options, select Search Server Options.

When you select Search Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **Extract text from binary** or right-click **Extract text from binary**, and then click **Enable** or **Disable**.

#### Task: Configure the full-text indexing schedule

Full-text indexing enables the creation and subsequent update of the full-text index.

You can schedule the indexing process to automatically start at a predetermined interval. The full-text indexing schedule is configured based on the indexing interval. The indexing interval specifies the time interval, in minutes, between the end of one indexing process and the start of the next indexing process. The default indexing interval is 60 minutes.

#### To configure the full-text indexing schedule

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Server Options**.
- 2. Under Server Options, select Search Server Options.

When you select Search Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **Indexing interval** or right-click **Indexing interval** and then click **Properties**.

The Indexing Interval dialog box appears.

Indexing Inte	rval		? 🛛
Computer Name: L	ocal Cor	nputer	
Indexing Interval:	50	*	minute(s)
			ОК Cancel

- 4. In the **Indexing Interval** dialog box, in the **Indexing Interval** box, type or select the number of minutes for the indexing interval.
- 5. Click **OK**.

#### Task: Configure a schedule for merge operations

Merge operations are used to combine temporary indexes into a permanent master index that is used for search queries. You can schedule the merging process to start at a predetermined interval. The schedule is configured based on the merge interval. The merge interval determines how often, in minutes, Search Server combines temporary indexes into a permanent master index, or in other words, updates the master index with new data during an indexing operation. By default, the merge is performed every 10 minutes. The range of values that you can specify is 1 to 1,000,000.

When specifying the merge interval, consider the following:

- A small merge interval will result in faster updates of the master index.
- You cannot perform full-text searches while merging is in progress.

#### To configure a schedule for merge operations

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Server Options**.
- 2. Under Server Options, select Search Server Options.

When you select Search Server Options in the console tree, they are displayed in the details pane.

3. In the details pane, double-click **Merge Interval** or right-click **Merge Interval** and then click **Properties**.

The Merge Interval dialog box appears.

Computer Name:	Local Cor	nputer	
Merge Interval:	10	*	minute(s)

- 4. In the **Merge Interval** dialog box, in the **Merge Interval** box, type or select the number of minutes for the merge interval.
- 5. Click **OK**.

#### Task: Rebuild the full-text index immediately

You can completely rebuild the full-text index immediately.

#### To rebuild the full-text index immediately

- 1. In the console tree, expand **DeviceLock Content Security Server**.
- Under DeviceLock Content Security Server, right-click Search Server, and then click Create New Index.

If the index already exists and you choose to create a new index, the following message box is displayed:

DeviceL	ock 🛛 🛛 🔀
2	Do you want to create the new index and overwrite the existing one (Yes - Overwrite, No - Append)?
	Yes No Cancel

In the message box, click **Yes** to completely rebuild the full-text index immediately. Click **No** to update the existing full-text index with changes immediately.

#### Task: Update the existing index immediately

If new data is added to DeviceLock Enterprise Server and you want to update the existing full-text index with these changes immediately, use the following procedure:

#### To update the existing index immediately

- 1. In the console tree, expand **DeviceLock Content Security Server**.
- 2. Under **DeviceLock Content Security Server**, right-click **Search Server**, and then click **Index Now**.

During an update operation, Search Server does not perform a full rebuild of the index. It indexes only new data on DeviceLock Enterprise Server in order to add new index entries to the existing index.

# Task: Monitor and refresh the status of the current indexing activity

Full-text indexing operations can be time-consuming and resource-intensive. Search Server lets you monitor the progress of the indexing operations that are currently being executed.

The indexing process happens in two stages. In the first stage, Search Server extracts significant words from shadow copies and log records and saves them to temporary indexes for each specified DeviceLock Enterprise Server. For each temporary index, Search Server processes 1,000 records from each log.

In the second stage, when either the number of temporary indexes becomes equal to 50 or 10 minutes pass, all temporary indexes are combined into a permanent master index that is used for search queries. The process of combining temporary indexes into a master index is called *merging*.

Search Server provides indexing and merging-related progress and status indicators.

# Indexing progress and status indicators

You can control the indexing process on each specified DeviceLock Enterprise Server by watching its status and progress counter. The status indicator shows the status of the indexing operation. The following table shows possible status values and their descriptions.

STATUS VALUE	DESCRIPTION
Idle	Indexing is not performed
Waiting	Waiting for indexing to begin
Indexing <log_name></log_name>	Indexing is in progress

The progress counter shows the percentage complete of the indexing process.

# Merging-related progress and status indicators

You can control the merge process by watching its status and progress counter. The status indicator shows the status of the merge operation. The following table shows possible status values and their descriptions.

STATUS VALUE	DESCRIPTION
Idle	The merge is not performed
Merging	The merge is in process
Defragmenting	Compressing (optimizing) the index. Compressing the index optimizes the index structure, removing obsolete data and defragmenting search structures for better performance.

The progress counter shows the percentage complete of the merge process.

# To monitor and refresh the status of the current indexing activity

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Search Server**.
- 2. Under Search Server, select Current Activity.

When you select Current Activity in the console tree, indexing and mergingrelated progress and status indicators are displayed in the details pane.

Because the status of the current indexing and merging-related operations is not updated automatically, you need to perform a refresh operation.

To perform a refresh operation, do one of the following:

• In the console tree, right-click **Current Activity**, and then click **Refresh**.

- OR -

In the console tree, select Current Activity, and then click Refresh and the toolbar.

- OR -

- In the console tree, select Current Activity. In the details pane, in the Name column, right-click any name of DeviceLock Enterprise Server or Merge Index, and then click Refresh.
   OR -
- In the console tree, select **Current Activity**. In the details pane, select the name of any DeviceLock Enterprise Server or **Merge Index**, and then click **Refresh** on the toolbar.

# **Using Search Server**

Using Search Server involves the following:

- Performing a full-text search operation
- Working with search results

# Performing a Full-Text Search Operation

With Search Server, you can locate every occurrence of a word or phrase in the DeviceLock Enterprise Server database. Because most searches return a large number of results, you can set search options to fine-tune and optimize your search. Search options specify how search results should be returned. Using search options, you can specify

- How many search results to return per page.
- How to filter the search results that are retrieved. Search results can be filtered by date and log. For example, you can limit the number of results to those within a certain date range and to those that are retrieved from certain logs.

Here are some notes to consider when using full-text search:

• Searches are not case sensitive.

You can search for words and phrases and use familiar wildcards such as asterisks (\*) and question marks (?) in search queries. An asterisk (\*) replaces an unlimited number of characters. The question mark (?) replaces a single character. You can use these wildcards in any position and in any quantity. To search for a specific phrase, enclose the phrase in double quotes. To search for multiple words, separate each word with a space. The following table shows the search items, examples, and results of these

SEARCH ITEM	EXAMPLE	RESULTS
Single word	price	Results that contain the word <b>price.</b> You will also find its grammatical variations, such as <b>prices</b> , <b>priced</b> and so on.
Phrase	confidential Results that contain both of the in- information words <b>confidential</b> and <b>informat</b> of the exact phrase.	
	"confidential information"	Results that contain the exact phrase confidential information.
Wildcard expression	te?t	Results that contain <i>test, text</i> , and so on.
Wildcard expression	mone*	Results that contain <i>money</i> , <i>monetary</i> , and so on.
Wildcard expression	*air	Results that contain <b>fair, impair, affair</b> , and so on.
Wildcard expression	* assets	Results that contain <b>monetary assets</b> , <b>liquid</b> <b>assets</b> , <b>fixed assets</b> , <b>current assets</b> , and so on.

#### To perform a search operation

types of searches.

- 1. In the console tree, expand **DeviceLock Content Security Server**, and then expand **Search Server**.
- 2. Under Search Server, select Search Page.

The search page is displayed in the details pane.

- 3. On the search page, in the **Search** box, type the word or phrase you want to find. To set search options, click **Options** and then do the following:
  - To specify the number of search results to display per page, in the Display...results per page list, click any of the following options: 10, 20, 30, 50, 100. The default number of returned results is 20.
  - To limit the scope of the search to specific data stores, select the appropriate check boxes under **Limit results to the following logs**. *By default, Search Server retrieves search results from the Audit Log, Shadow Log, and Deleted Shadow Log.*

• To filter search results by date, specify a date range that limits the data retrieved from the data sources. To do so, set the following date parameters:

PARAMETER	DESCRIPTION	
From	Specifies the beginning of the date range in which to search. Possible values: <b>First Record</b> or <b>Records On</b> . The default value is <b>First Record</b> .	
	First Record causes Search Server to retrieve data starting with the first record written to the log.	
	<b>Records On</b> causes Search Server to retrieve data that was written starting with a specific date.	
То	Specifies the end of the date range in which to search. Possible values: Last Record or Records On. The defair value is Last Record.	
	<b>Last Record</b> causes Search Server to retrieve data ending with the last record written to the log.	
	<b>Records On</b> causes Search Server to retrieve data that was written ending with a specific date.	

If you set the date parameters to **Records On**, click in the **From** and **To** boxes to display the calendar. In the calendar, click to select the day. You can use single arrows (<>) to change what month you view and double arrows (<<>>) to change what year you view.

4. Click **Search**.

# Working with Search Results

Working with search results involves the following:

- Interpreting search results
- Manipulating search results retrieved from the Shadow Log

# Interpreting search results

After you enter search criteria and submit you search, Search Server returns the search results page which looks like this.

customer	Search Options >	>
		Results 1 - 3 for customer.
<ol> <li>16:12:28 Success vm2003ser database.doc 27,5 KB TANYA</li> <li>Log Parameters 9/28/2009 4:12:28 PM Deleted Shadow Data Log</li> </ol>	ver.testlabdc.com Removable \DC\Administrator 2864 C:\WI	Write G:\ <b>Customer</b> INDOW5
<ol> <li>16:12:28 Success vm2003ser database.doc 27,5 KB TANYA</li> <li>■ Log Parameters 9/28/2009 4:12:28 PM Deleted Shadow Data Log</li> </ol>	ver.testlabdc.com Removable NDC\Administrator 2864 C:\WI	Write G:\ <b>Customer</b> INDOWS
<ul> <li>3. 16:12:28 Success vm2003ser database.doc 27,5 KB TANYA</li> <li>         Elog Parameters</li></ul>	ver.testlabdc.com Removable NDC\Administrator 2864 C:\WI	Write G:\ <b>Customer</b> INDOWS
	1	

The search results page is divided into the following viewing areas:

- Search query Displays the search criteria you entered.
- **Statistics bar** Shows the number of results displayed on the current search results page.
- **Search results** Displays a numbered list of items containing information that matched the search criteria you entered.
- **Results navigator** Shows how many results pages are returned and allows you to navigate from page to page.

Each of these areas is described in more detail below.

#### Search query

This area is located at the top of the search results page. Click **Options** to view additional search criteria you specified.

customer	Search	Options <<	
Display 10 💌 results per page			
Limit results to the following logs:			
Audit Log			
Shadow Log			
Deleted Shadow Data Log			
Server Log			
Monitoring Log			
<u> </u>			
Limit results to the following date range:			
From: First Record -			
To: Last Record V			

#### Statistics bar

This area is located immediately above the search results area and looks like this.

Results 1 - 3 for customer.

# Search results

This area is located below the search query area and statistics bar and looks like this.

1.	16:12:28 Success vm2003server.testlabdc.com Removable Write G:\ <b>Customer</b> database.doc 27,5 KB TANYADC\Administrator 2864 C:\WINDOWS Log Parameters 9/28/2009 4:12:28 PM Deleted Shadow Data Log
2.	16:12:28 Success vm2003server.testlabdc.com Removable Write G:\ <b>Customer</b> database.doc 27,5 KB TANYADC\Administrator 2864 C:\WINDOWS Description: 9/28/2009 4:12:28 PM Deleted Shadow Data Log
3.	16:12:28 Success vm2003server.testlabdc.com Removable Write G:\Customer database.doc 27,5 KB TANYADC\Administrator 2864 C:\WINDOWS <u>Log Parameters</u> <u>Document Parameters</u> 9/28/2009 4:12:28 PM - 27Kb - Shadow Log <u>Open - Save - View</u>

A search result includes the following:

• **Snippets** – portions of text containing highlighted query words (bold font). These snippets allow you to see the context in which the query words were found. The search results page displays only the first three snippets per search result.

Log Parameters – summary information retrieved from the log for this search result. Click the plus sign (+) to expand Log Parameters and view this information. This information is different, depending on the log type.

**Note:** If an entry in a log has an empty field, this field is not displayed in **Log Parameters**.

The following information is displayed in **Log Parameters** for a result retrieved from the Audit Log:

- Received Date/Time the date and time when the event was received by DeviceLock Enterprise Server.
- Type the class of the event, either Success for allowed access or Failure for denied access. This value matches the value in the Type column of the server's Audit Log Viewer.
- **Computer** the name of the computer from which the Audit Log was received. This value matches the value in the **Computer** column of the server's Audit Log Viewer.
- **Date/Time** the date and time when the event was received by DeviceLock Service. This value matches the value in the **Date/Time** column of the server's Audit Log Viewer.
- **Source** the type of device or protocol involved. This value matches the value in the **Source** column of the server's Audit Log Viewer.
- Action the user's activity type. This value matches the value in the Action column of the server's Audit Log Viewer.
- **Name** the name of the object (file, USB device, etc.). This value matches the value in the **Name** column of the server's Audit Log Viewer.
- **Information** other device-specific information for the event, such as the access flags, device names, and so on. This value matches the value in the **Information** column of the server's Audit Log Viewer.
- **User** the name of the user associated with this event. This value matches the value in the **User** column of the server's Audit Log Viewer.
- **PID** the identifier of the process associated with this event. This value matches the value in the **PID** column of the server's Audit Log Viewer.
- **Process** the fully qualified path to the process executable file. In some cases, the process name may be displayed instead of the path. This value matches the value in the **Process** column of the server's Audit Log Viewer.
- **Event** the number identifying the event type. This value matches the value in the **Event** column of the server's Audit Log Viewer.

The following information is displayed in **Log Parameters** for a result retrieved from the Shadow Log or Deleted Shadow Data Log:

• **Received Date/Time** - the date and time when the data was received by DeviceLock Enterprise Server.

- **Status** the status of the record. The **Success** status indicates that data is successfully logged; the **Incomplete** status indicates that data is possibly not completely logged while the **Failed** status is given to shadow copies of files whose transmission was blocked by Content-Aware Rules. This value matches the value in the **Status** column of the server's Shadow Log Viewer.
- Computer the name of the computer from which the Shadow Log was received. This value matches the value in the Computer column of the server's Shadow Log Viewer.
- **Date/Time** the date and the time when the data was transferred. This value matches the value in the **Date/Time** column of the server's Shadow Log Viewer.
- **Source** the type of device or protocol involved. This value matches the value in the **Source** column of the server's Shadow Log Viewer.
- Action the user's activity type. This value matches the value in the Action column of the server's Shadow Log Viewer.
- **File Name** the original path to the file or the auto-generated name of the data that originally was not a file (such as CD/DVD images, data written directly to the media or transferred through the serial/parallel ports). This value matches the value in the **File Name** column of the server's Shadow Log Viewer.
- File Size the size of the data. This value matches the value in the File Size column of the server's Shadow Log Viewer.
- User the name of the user who transferred the data. This value matches the value in the User column of the server's Shadow Log Viewer.
- **PID** the identifier of the process used to transfer the data. This value matches the value in the **PID** column of the server's Shadow Log Viewer.
- **Process** the fully qualified path to the process executable file. In some cases, the process name may be displayed instead of the path. This value matches the value in the **Process** column of the server's Shadow Log Viewer.

The following information is displayed in **Log Parameters** for a result retrieved from the Server Log:

- Type the class of the event: Success, Information, Warning or Error. This value matches the value in the Server Log Viewer's Type column.
- **Date/Time** the date and time when the event occurred. This value matches the value in the Server Log Viewer's **Date/Time** column.
- **Event** the number identifying the event type. This value matches the value in the Server Log Viewer's **Event** column.
- Information event-specific information, such as error/warning descriptions, names and values of changed parameters, and so on. This value matches the value in the Server Log Viewer's Information column.
- **Server** the name of the server where the event occurred. This value matches the value in the Server Log Viewer's **Server** column.

 Record N – the record number. This value matches the value in the Server Log Viewer's Record N column.

The following information is displayed in **Log Parameters** for a result retrieved from the Monitoring Log:

- Type the class of the event: Success, Information, Warning or Error. This value matches the value in the Type column of the server's Monitoring Log Viewer.
- **Date/Time** the date and time when the event occurred. This value matches the value in the **Date/Time** column of the server's Monitoring Log Viewer.
- **Event** the number identifying the event type. This value matches the value in the **Event** column of the server's Monitoring Log Viewer.
- **Task Name** the name of the task responsible for this event. Can be empty if the event does not link to any task. This value matches the value in the **Task Name** column of the server's Monitoring Log Viewer.
- **Computer Name** the name of the computer belonging to the task that is responsible for this event. Can be empty if the event does not link to the computer. This value matches the value in the **Computer Name** column of the server's Monitoring Log Viewer.
- **Information** event-specific information, such as status, error, warning, and so on. This value matches the value in the **Information** column of the server's Monitoring Log Viewer.
- **Server** the name of the server where the event occurred. This value matches the value in the **Server** column of the server's Monitoring Log Viewer.
- Record N the record number. This value matches the value in the Record N column of the server's Monitoring Log Viewer.
- Document Properties summary information retrieved from the document properties for this search result. This information is retrieved randomly and is displayed only for shadow copies. Click the plus sign (+) to expand Document Properties and view this information. This information is different, depending on the file type. For example, the following information is displayed in Document Properties for a shadow copy of a Word document:
  - **Application:** Microsoft Office Word.
  - **Author:** the name of the user who created the document.
  - **Created:** the date and time when the document was created.
  - **LastSaved:** the date and time when the document was last saved.
  - LastSavedBy: the name of the user who last saved the document.
  - **RevisionNumber:** the number of times the document has been saved.
  - **Template:** the name of the template attached to the document.
  - **Title:** the name of the document.
  - **TotalEditingTime:** the number of minutes that the document has been opened for making changes since it was created.
- The date and time when the log entry was created.
- **The size of the log entry**. This value is displayed only for shadow copies retrieved from the Shadow Log.
- The name of the log in which matches of the query occurred.
- Open, Save and View links allow you to access and manipulate the search results (shadow copies) retrieved from the Shadow Log. For detailed information on how to manipulate shadow copies, see <u>Manipulating search</u> results retrieved from the Shadow Log."

**Note:** If your search produced no results, the search results page displays a message indicating that no matches were found.

#### **Results navigator**

This area is located at the bottom of the search results page and looks like this.

Previous 1 2 3 4 5 6 7 8 9 10 Next

To move forward or backward through your results, click **Next** or **Previous** or click the page number.

#### Manipulating search results retrieved from the Shadow Log

You can perform the following operations on results retrieved from the Shadow Log:

- Open a shadow copy of a file in its native application.
- Save a shadow copy of a file to any local or network location.
- Open and save a shadow copy of a file using the built-in viewer.

Below are step-by-step instructions demonstrating how to perform these operations.

#### To open a shadow copy of a file in its native application

- 1. Perform your search.
- 2. On the search results page, click **Open** under the desired search result.

The shadow copy of the file opens in its native application.

*If there is no native application, the Open With dialog box appears. Use this dialog box to choose the program with which to open the file.* 

*If you open the shadow copy of a file captured from either Printer or Parallel port device types, it always opens in the built-in DeviceLock Printer Viewer.* 

DeviceLock Printer Viewer is able to display a shadowed printed document in native print spooler format, to send it to the printer again, or save it as a graphics file (such as BMP, GIF, JPEG, PNG, EMF or TIFF). The following print spooler formats are supported: PostScript, PCL5, PCL6 (PCL XL), HP-GL/2, GDI printing (ZjStream) and EMF Spooled Files.

#### To save a shadow copy of a file to any local or network location

1. Perform your search.

2. On the search results page, click **Save** under the desired search result.

The Save As dialog box appears.

- 3. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the shadow copy.
- 4. In the **File name** box, type the file name you want.
- 5. Click Save.

If the data was transferred by the user as a file, it is stored in the shadow log as a file and can be saved to the local computer as a file too.

When a user has written data to a CD/DVD disk, all data is stored in the shadow log as a single CD/DVD image (one image per each written CD/DVD disk or session) in the CUE format.

*CD/DVD images as well as other data that originally was not transferred as files (direct media access or serial/parallel ports transfer), have auto-generated names based on the action's type, drive's letter or device's name and time/date (for example, direct\_write(E:) 19:18:29 17.07.2006.bin).* 

Each CD/DVD image is saved to the local computer as two files: the data file with the .bin extension (for example, direct\_write(E\_) 19\_18\_29 17\_07\_2006.bin) and the cue sheet file that has the same name as its data file with the .cue extension (for example, direct\_write(E\_) 19\_18\_29 17\_07\_2006\_bin.cue). Both these files are necessary to open the CD/DVD image in the external application that supports the CUE format (such as Cdrwin, Nero, DAEMON Tools, IsoBuster, UltraISO, WinISO and many others).

#### To open and save a shadow copy of a file using the built-in viewer

- 1. Perform your search.
- 2. On the search results page, click **View** under the desired search result.

The shadow copy opens in the built-in viewer.

- 3. In the built-in viewer, click any of the following viewing options:
  - **Hex** Displays data in hex as well as in words.
  - **Autodetect Text** Enables the auto-detection of encoding for text and displays data in textual format only.
  - **ANSI Text** Specifies ANSI encoding for text and displays data in textual format only.
  - **UTF-16 Text** Specifies Unicode UTF-16 encoding for text and displays data in textual format only.
  - **UTF-16BE Text** Specifies Unicode UTF-16 (Big Endian) encoding for text and displays data in textual format only.

To save the file, click **Save** to open the **Save As** dialog box. In the **Save As** dialog box, do the following:

- In the **Save in** box, browse to the location where you want to save the file.
- In the **File name** box, type the file name you want.
- Click Save.

4. Click **Close** to close the viewer.

# **DeviceLock Group Policy Manager**

## Overview

In addition to the standard way of managing permissions via <u>DeviceLock Management</u> <u>Console</u>, DeviceLock also provides you with a more powerful mechanism – settings can be changed and deployed via Group Policy in an Active Directory domain. System administrators can use policies to control DeviceLock's configurations from a single location on a network – no matter how large the network.

Group Policy enables policy-based administration that uses Active Directory. Group Policy uses directory services and security group membership to provide flexibility and support extensive configuration information. Policy settings are created using the Microsoft Management Console (MMC) snap-in for Group Policy.

Tighter integration into Active Directory is a very important function of DeviceLock. It makes DeviceLock's management and deployment easier for large networks and more convenient for system administrators.

Integration with Active Directory eliminates the need to install more third-party applications for centralized management and deployment. DeviceLock does not need to have its own server-based component to control the entire network, instead it uses standard functions provided by Active Directory.

Via Group Policy it is possible to:

- Install DeviceLock Service on all the computers on a network, even those that are not currently running and new computers that are just connecting to the network.
   For more information regarding DeviceLock Service deployment, see "Installation via Group Policy."
- Control and configure DeviceLock Service on a large number of computers in different domains/organizational units simultaneously.
   Even if some computers are not currently running or they are new computers that are just connecting to the network, they are included in DeviceLock's automatic deployment of predefined settings.
- View the policy currently being applied and predict what policy would be applied. For more information, see "<u>Using Resultant Set of Policy (RSoP</u>."

**Note:** In order to manage DeviceLock via Group Policy, you must have Active Directory properly installed and configured. For more information about installing and configuring Active Directory, please refer to the related Microsoft documentation.

# **Applying Group Policy**

Policy is applied when the computer starts up. When a user turns on the computer, the system applies DeviceLock's policy.

Policy can be optionally reapplied on a periodic basis. By default, policy is reapplied every 90 minutes. To set the interval at which policy will be reapplied, use the Group Policy Object Editor. For more information, please refer to the Microsoft Knowledge Base: <a href="http://support.microsoft.com/default.aspx?scid=kb;en-us;203607">http://support.microsoft.com/default.aspx?scid=kb;en-us;203607</a>.

Policy can also be reapplied on demand. To refresh the current policy settings immediately on Windows XP and later, administrators can call the **gpupdate.exe** /force command-line utility provided by Microsoft. On Windows 2000, administrators can call another command-line utility provided by Microsoft: **secedit** /refreshpolicy machine\_policy /enforce.

When applying policy, the system queries the directory service for a list of Group Policy Objects (GPOs) to process. Each GPO is linked to an Active Directory container to which the computer or user belongs. By default, the system processes the GPOs in the following order: local, site, domain, then organizational unit. Therefore, the computer receives the policy settings of the last Active Directory container processed.

When processing the GPO, the system checks the access-control list (ACL) associated with the GPO. If an access-control entry (ACE) denies the computer access to the GPO, the system does not apply the policy settings specified by the GPO. If the ACE allows access to the GPO, the system applies the policy settings specified by the GPO.

# **Standard GPO Inheritance Rules**

Any unconfigured settings anywhere in a GPO can be ignored since they are not inherited down the tree; only configured settings are inherited. There are three possible scenarios:

- A parent has a value for a setting, and a child does not.
- A parent has a value for a setting, and a child has a non-conflicting value for the same setting.
- A parent has a value for a setting, and a child has a conflicting value for the same setting.

If a GPO has settings that are configured for a parent Organizational Unit, and the same policy settings are unconfigured for a child Organizational Unit, the child inherits the parent's GPO settings. That makes sense.

If a GPO has settings configured for a parent Organizational Unit that do not conflict with a GPO on a child Organizational Unit, the child Organizational Unit inherits the parent GPO settings and applies its own GPOs as well.

If a GPO has settings that are configured for a parent Organizational Unit that conflict with the same settings in another GPO configured for a child Organizational Unit, then the child Organizational Unit does not inherit that specific GPO setting from the parent Organizational Unit. The setting in the GPO child policy takes priority, although there is one case in which this is not true.

If the parent disables a setting and the child makes a change to that setting, the child's change is ignored. In other words, the disabling of a setting is always inherited down the hierarchy.

## Starting DeviceLock Group Policy Manager

DeviceLock Group Policy Manager integrates into the Windows Group Policy Object (GPO) editor. To use DeviceLock Group Policy Manager on your local PC rather than on the domain controller, you need to have the GPO editor installed locally. We recommend that you install the Group Policy Management Console (GPMC). It can be downloaded from the <u>Microsoft Download Center</u>.

To open DeviceLock Group Policy Manager, you should run the GPO editor first:

1. Start the Group Policy Management snap-in.

*If the Group Policy Management snap-in is not installed on your computer, you may use the Active Directory Users and Computers snap-in instead.* 

2. In the console tree, select your domain.



 Select the group policy object that you need, and then click **Edit** on the context menu available by a right mouse click. If you wish to create a new group policy object, click **Create and Link a GPO Here** on the context menu of the selected domain.

If you are using the Active Directory Users and Computers snap-in, right-click your domain, then click **Properties**.

4 Active Directory Users and Com	puters	
🛛 🎻 Console 🛛 Window 🛛 Help		_8×
Tree	sl2.com 5 objects	
Active Directory Users and Computer	Name Ruiltin Iters n Controllers SecurityPrincipal	Type builtinDomain Container Organizational Unit Is Container Container

Click the **Group Policy** tab, select the group policy object that you need, and then click **Edit**. If you wish to create a new group policy object, click **Add**.

Active Directory Us	ers and Computers	
] 🎻 <u>C</u> onsole <u>W</u> indow	sl2.com Properties	? ×
Tree Active Directory Users	General Managed By Group Policy	[
E-BJ sl2.com B-Builtin B-Builtin B-Builtin	Current Group Policy Object Links for sl2	
E 🙆 Domain Contro	Group Policy Object Links No 0	Override Disabled
ForeignSecurit	🚮 Default Domain Policy	×
	Group Policy Objects higher in the list have the highest This list obtained from: sl_server2.st2.com <u>New</u> Add Edit <u>Options</u> Delete Properties	priority.
	1 Block Londy Intervalue	
	OK Cano	el <u>Apply</u>

4. Wait until the GPO editor is started.

It may take up to several seconds.

5. Under Computer Configuration, select DeviceLock.



Alternatively, to run the GPO editor you can start MMC and add the Group Policy snap-in manually:

- 1. Run **mmc** from the command line or use the **Run** menu to execute this command.
- 2. On the File menu, click Add/Remove snap-in.

ħ	Console1 - [(	Consol	e Root]			
ĩ	Eie Action	⊻iew	Favorites	Window	Help	_ & ×
± 1	New Open Save As Add/Remove Options 1 C:\downlow 2 C:\WINDO 3 DeviceLock 4 DeviceLock Exit	= Snap-I ads\Gro WS\\ : Manag : Manag	n up Policy.msr compmgmt.m ement.msc iement.msc	Ctrl+N Ctrl+O Ctrl+S Ctrl+M		Name There are no items to show in this view.
Adds	s or removes indi	vidual s	nap-ins.			,

3. In the **Add/Remove snap-in** dialog box, click the **Standalone** tab, and then click **Add**.

tandalone Extens	sions	
Use this page to ad	dd or remove a standalone Snap-in from the console.	52
Snap-ins added to:	🔄 Console Root 🛛 🗸	2
Description		
Description		
Description	Remove About	

4. Select **Group Policy** from the list, then click **Add**.

ê (	Add/Remove Snap-	n	? 🗙 🖃	<
	Standalone Extensio	8		
	Use this page to add <u>Snap-ins</u> added to:	or remo Add Standalone Snap-	-in o-ins:	
		Snap-in	Vendor	^
		Disk Defragmenter Disk Management Event Viewer Folder Group Policy Indexing Service IP Security Monitor IP Security Policy Mar Link to Web Address	Microsoft Corp. E Microsoft and VE Microsoft Corpora Microsoft Corpora Microsoft Corpora Microsoft Corpora Microsoft Corpora Microsoft Corpora Microsoft Corpora	xecutive { RITAS Sc ation ation ation, Inso ation ation
	Add	Description This snap-in allows you to to a Site, Domain, or Orga on a computer.	edit Group Policy Objects which c nizational Unit in the Active Direct	an be linked ory or stored

5. Select a Group Policy Object either from Active Directory or a local computer, and then click **Finish**.

Select Group Policy Object	X
Welcome to the Group Policy Wize	ard
	Group Policy Objects can be stored in the Active Directory or on a local computer. Use the Browse button to select a Group Policy Object. Group Policy Object: Remote computer: s_server2 Browse
	only applies if you save the console.

- 6. Click **Close** to close the **Add Standalone Snap-in** window.
- 7. Click **OK** to add the snap-in.
- 8. Expand the **Computer Configuration** container, and then select **DeviceLock**.

### **Using DeviceLock Group Policy Manager**

There is almost no difference between the procedure of managing DeviceLock Service via DeviceLock Management Console and via DeviceLock Group Policy Manager. For more information, see "<u>Managing DeviceLock Service</u>."

🚡 Group Policy Object Editor	
Eile Action View Help	
← → 🗈 📧 🛱 😤 🔡 😫 ?	
DeviceLock Group Policy Object [vm2000server.vm2000ad.com]     Generation     Software Settings     Mindows Settings     Administrative Templates     Smartline DeviceLock     User Configuration	Policy Name
, ,	vm2000server.vm2000ad.

It is impossible to manage DeviceLock Enterprise Server and view audit and shadow logs using DeviceLock Group Policy Manager. For such operations you should use <u>DeviceLock</u> <u>Management Console</u>.

DeviceLock Service management via DeviceLock Group Policy Manager includes four additional features in comparison to DeviceLock Management Console:

 Override Local Policy – If you want to disallow changing settings, permissions and audit rules for individual computers (without the GPO editor), enable Override Local Policy in Service Options. This enables the Group Policy mode for all the computers in GPO, so that the Local Policy mode cannot be enabled for these computers.

🚡 Group Policy Object Editor		-OX
Eile Action View Help		
Comp Policy Object [vm2000serve	Name	State
Gomputer Configuration     Gomputer Settings	BeviceLock Administrators	Not Configured
Windows Settings     Administrative Templates     Smartline DeviceLock     Service Options     Devices	USB/FireWire blocked message Expired message	Not Configured Not Configured
	DeviceLock Enterprise Server(s) Log policy changes and Start/Stop events	Not Configured Not Configured
User Configuration	DeviceLock certificate	Not Configured Enabled
	vm2000server.vm2000ad.	

*If the Override Local Policy parameter is enabled, it means that the Use Group Policy parameter in Service Options of DeviceLock Management Console and DeviceLock Enterprise Manager cannot be disabled.* 

The following table shows how different settings of the **Use Group Policy** parameter and the **Override Local Policy** parameter affect the policy application mode:

POLICY APPLICATION MODE	USE GROUP POLICY	OVERRIDE LOCAL POLICY
Only Local Policy is applied.	Disabled	Disabled
Only Group Policy is applied.	Enabled	Enabled
Local Policy is applied until Active Directory replication occurs.	Enabled	Disabled

When setting the **Override Local Policy** parameter, consider the following:

- Disabling the **Override Local Policy** parameter does not cancel Active Directory replication.
- If the **Override Local Policy** parameter is disabled, all DeviceLock Service settings that you set via DeviceLock Management Console and DeviceLock Enterprise Manager take effect immediately.

 Undefine – You can reset any parameter to the unconfigured state. All undefined parameters are ignored in this GPO. For more information, see "<u>Standard GPO</u> <u>Inheritance Rules</u>."



Use **Undefine** from the context menu of any parameter to reset this parameter to the unconfigured state. Also, for some parameters, you can use the intermediate state (gray) of the check box to make it unconfigured.

👔 Blocked Message	? ×
Computer Name: vm2000server.vm2000ad.com	
🔽 Enable USB/FireWire Blocked Message	
Blocked Message <u>C</u> aption:	

 Undefine entire policy – You can reset all parameters to the unconfigured state in one click. Selecting this has the same effect as resetting each parameter one by one (see above).

🚡 Group Policy Object Edite	Dr		_O×
Eile Action View Help	? 📑 😫 🖓		
DeviceLock Group Policy Ob Omputer Configuration Omputer Configuration Omputer Settings Omputer Settings Omputer Settings Omputer Settings	iect [vm2000serve	Name Service Options Devices	
⊕ Smartline DeviceLo	Certificate Gener Temporary White	ration Tool e List Administration Tool	
	Undefine entire p	policy	
	About DeviceLoc	k	
	⊻iew		•
	Export List		
Resets the entire DeviceLock c	Help		

Use **Undefine entire policy** from the context menu of **DeviceLock** to reset all parameters to the unconfigured state.

DeviceLo	ck 🔀
1	Undefining the entire DeviceLock group policy is an irreversible action. All DeviceLock settings will be lost.
	Are you sure you want to continue?
	Yes No

4. **Remove Offline** - You can remove any offline policy settings (permissions, audit and shadowing rules, white lists, etc.) for both devices and protocols in order to enforce regular ones in this GPO. To do so, right-click any policy setting, and then click **Remove Offline**.

**Note:** In order to manage DeviceLock Service settings via Group Policy, DeviceLock Service must be installed and started on all the computers belonging to the GPO. For more information about the service installation, see "Deploying DeviceLock Service."

Also, do not forget that Group Policy is reapplied on a periodic basis (by default, every 90 minutes) so your changes do not take effect immediately. For more information, see "<u>Applying Group Policy</u>."

### Using Resultant Set of Policy (RSoP)

DeviceLock supports Resultant Set of Policy so you can use the standard Windows snap-in to view the DeviceLock policy currently being applied, as well as to predict what policy would be applied to a chosen computer.

To use RSoP, you should start MMC and add the Resultant Set of Policy snap-in manually:

- 1. Run **mmc** from the command line or use the **Run** menu to execute this command.
- 2. On the **File** menu, click **Add/Remove snap-in**.

6	Console1 - [Console Root]			
ĩ	Ele Action View Favorites	₩indow	Help	_ & ×
1	New Open Save Save As Add/Remove Snap-in Options 1 C:\downloads\Group Policy.msc 2 C:\WINDOWS\\compmgmt.m 3 DeviceLock Management.msc 4 DeviceLock Management.msc Exit	Ctrl+N Ctrl+O Ctrl+S Ctrl+M		Name There are no items to show in this view.
Adds	or removes individual snap-ins.			

- 3. Click the **Standalone** tab, and then click **Add**.
- 4. Select **Resultant Set of Policy** from the list, then click **Add**.

vailable Standalone Snap-ins:		
Snap-in	Vendor	^
R IP Security Monitor	Microsoft Corporation	
R IP Security Policy Management	Microsoft Corporation	
Link to Web Address	Microsoft Corporation	
Local Users and Groups	Microsoft Corporation	
Performance Logs and Alerts	Microsoft Corporation	
Remote Desktops	Microsoft Corporation	1991
🔂 Remote Storage	Microsoft Corporation	
Premovable Storage Management	Microsoft Corporation	
SResultant Set of Policy	Microsoft Corporation	
Security Configuration and Analysis	Microsoft Corporation	~
Description This snap-in allows you to view the Result nachine. The snap-in can be used to vie as well as predict what policy would be ap	ant Set of Policy for a use w policy that has been ap plied to a user on a mach	r on a plied ine.

- 5. Click **Close** to close the **Add Standalone Snap-in** window and then click **OK** to add the snap-in.
- 6. In the console tree, select **Resultant Set of Policy**.

🚡 Console1 - [Console Ro	ot\Resultant Set of Policy]	
🚡 File Action View Fav	rorites Window Help	<u>X</u>
⇔ ⇒ 🗈 🖬 🔮		
Console Root	S Resultant Set of Policy	
	Generate RSoP Data	
	View New Window from Here	Action required
	New Taskpad View	Select 'Generate RSoP Data'
	Help	from the Action menu.
	Extended Standard	l
Launches a wizard to obtain Res	ultant Set of Policy information.	

- 7. Click **Generate RSoP Data** on the context menu available by a right mouse click.
- 8. Go through the Resultant Set of Policy Wizard to obtain RSoP information from the selected computer.

9. Expand the **Computer Configuration** container, and then select **DeviceLock**.

🚡 Console1 - [Console Root\XPVIF	T - RSoP\Computer Configuration	NS 💶 🗖
File Action View Favorites W ← → € III E, 12 ?	ndow Help	<u>_8×</u>
Console Root Console Root Computer Configuration Computer Configuration Co	Name Service Options Devices	
	XPVIRT	

Please note that using RSoP you cannot modify the policy – all parameters are in the readonly mode.

RSoP is very useful when you need to understand which particular GPO will be applied to the computer.

For more information on Resultant Set of Policy, please refer to the Microsoft's on-line article: <u>http://technet.microsoft.com/en-us/library/cc775741%28WS.10%29.aspx</u>.

# **DeviceLock Service Settings Editor**

### **Overview**

DeviceLock Service Settings Editor is used for creating and modifying external XML files with settings, permissions, audit and shadowing rules for DeviceLock Service.

DeviceLock Service Settings Editor installs together with the other management consoles.

File     Action     View     Help       ←     →     III     III     III	Se DeviceLock Service Settings Editor	
Smartline DeviceLock Settings	File       Action       View       Help            ←         →         ①         ①         ②         Smartline DeviceLock Settings           ②         ③         DeviceLock Settings             ③         DeviceLock Setvice           ③         DeviceLock           Undefine entire polic         Load Service Setting         Save Service Setting             ④         DeviceLock           DeviceLock           Undefine entire polic         Load Service Setting             ①         Auditing & S           Save Service Generatic           Save & Sign Service             ①         Devices           DeviceLock           Certificate Generatic             ①         Devices           Devices           About DeviceLock             ③         Devices           UISB Device:           Help             ③         Security Settings           Security Settings	Name Ck Service gs Settings on Tool

There is almost no difference between the procedures for defining policies via DeviceLock Management Console versus via DeviceLock Service Settings Editor. For more information, see "<u>Managing DeviceLock Service</u>."

In comparison to DeviceLock Management Console, in DeviceLock Service Settings Editor:

- You do not need to connect to any computer with DeviceLock Service. DeviceLock Service Settings Editor modifies and stores settings in external XML files and allows you to create/edit policies offline. It works similar to DeviceLock Group Policy Manager but instead of GPOs it uses XML files.
- You can reset any parameter (or all parameters at once) to the unconfigured state. All undefined parameters are ignored when the policy is applied to DeviceLock Service.
- You can remove any offline policy settings (permissions, audit and shadowing rules, white lists, etc.) for both devices and protocols in order to enforce regular ones in this policy file.

To create a new policy from scratch, just run DeviceLock Service Settings Editor and start making changes in its default (empty) policy.

If you want to modify an existing policy, you should load the XML file with that policy to DeviceLock Service Settings Editor using the **Load Service Settings** context menu command and then make desired changes.

If you create a new policy from scratch, you should use **Save Service Settings** from the context menu to save it in an XML file. Alternatively, you can use **Save & Sign Service Settings** from the context menu to save the policy to an external XML file and automatically sign it with the most recent DeviceLock Certificate (the private key). The **Save & Sign Service Settings** command is unavailable when the DeviceLock Signing Tool has no previously loaded private key.

Later files with policies created using DeviceLock Service Settings Editor can be loaded via DeviceLock Management Console and/or DeviceLock Group Policy Manager.

Also, files with policies can be sent to users whose computers are not online and thus outof-reach via management consoles. To avoid unauthorized modification these files should be signed with the DeviceLock Certificate (the private key) using the DeviceLock Signing Tool. For more information, see "<u>Service Settings</u>."

If you modify an existing policy file, DeviceLock Service Settings Editor automatically saves your changes.

**Note:** Only settings that are explicitly defined in a policy file apply to client computers. All policy settings that have the **Not Configured** state are ignored by client computers.

DeviceLock Service Settings Editor is also used in the Set Service Settings plug-in of DeviceLock Enterprise Manager. This plug-in runs DeviceLock Service Settings Editor as an external application and opens it with the XML file selected in the plug-in's settings dialog box.

When you make any policy changes (change parameters, set permissions, define white lists, etc.) in the XML file passed to the editor by the plug-in, DeviceLock Service Settings Editor automatically saves them to this file. As soon as you finish modifying the policy just close DeviceLock Service Settings Editor and return to the plug-in's settings dialog box.

For more information, see "Set Service Settings."

# **DeviceLock Enterprise Manager**

### Overview

With DeviceLock Enterprise Manager, you can view and change security policies defined for device types and protocols; install, update and uninstall DeviceLock Service; and view audit and shadow logs for all the computers in a large network. We recommend using DeviceLock Enterprise Manager if you have a large network without Active Directory.

Based on a multi-threaded engine, using this console speeds up all activity for all the computers in the large network.

DeviceLock Enterprise Manager stores, compares and filters the data it receives from all the computers. Administrators can make "snapshots" of the systems for future comparison and notation of changes.

DeviceLock Enterprise Manager has a flexible plug-in based architecture that allows you to plug in necessary modules on demand. Each module (plug-in) performs a task and displays retrieved information in its own window.

For information on how to install DeviceLock Enterprise Manager, please read the <u>Installing</u> <u>Management Consoles</u> section of this manual.

To run DeviceLock Enterprise Manager, select the appropriate shortcut from the **Programs** menu available by clicking the Windows **Start** button.



### Interface

DeviceLock Enterprise Manager has a Multi Document Interface (MDI) structure, allowing you to keep each task in its own window.

The main window of DeviceLock Enterprise Manager can be resized. DeviceLock Enterprise Manager saves its size and position, and restores these at its next startup.

There is a menu at the top of the main window. Many functions are accessible through this menu.

2	Devi	ceLocl	k Enterpr	ise Manager
Ł.	<u>F</u> ile	⊻iew	<u>W</u> indow	<u>H</u> elp



To change the columns displayed in the plug-in's windows, click **Select Columns** on the **View** menu or click the appropriate button on the **Main** toolbar.

By default, DeviceLock Enterprise Manager displays information received from the plug-ins in the form of a tree. However, information can also be displayed as a plain list. To change the mode, point to **View Mode** on the **View** menu and click either **Tree** or **List**. Please note that View Mode must be set for each plugin individually.

You can hide the status bar and/or the log window by deselecting appropriate items on the **View** menu.

To enable the gridlines around items in the plug-in's window, click **Enable Grid** on the **View** menu. This mode sets for each plug-in individually.



To sort data in any plug-in's window, click the column heading you want to sort by. To reverse the sort order, click the

column heading a second time.

If you need to sort the top-level tree's items (such as domains and computers), use appropriate buttons on the **Main** toolbar.



There is a log window at the bottom of the main window. The log window is used to display useful information about ongoing activity as well as diagnostic and error messages. There are two log lists: **Information** and **Warnings/Errors**.

You can click the right mouse button on the log window to open the useful

Log Window			x
Plug-in	•	Enable Grid	
Report Permissions/Auditin		Save As	2
Information Warnings/Errors	<b>–</b>	Keep Last Message in View Set Message Count	H
		Disable Log	
	×	Clear All	



context menu.

## Scan Network Dialog Box

The **Scan Network** dialog box allows you to select computers on your network and the action (install or remove DeviceLock Service, set permissions, and so on) which should be performed for these computers.

🛃 Scan Network	<u>?</u> ×
Select computer(s) from the LDAP LDAP LDAP ID	tree Select Plug-in  Select Plug-in  Audit Log Viewer  Select Plug-in  Audit Log Viewer  Select Parmissions/Auditing  Report ParP Devices  Set Service Settings  Shadow Log Viewer  Uninstall service
	Settings
Show this dialog at next startup	Scan Close

To open the **Scan Network** dialog box, click **Scan Network** on the **File** menu or press the appropriate button on the **Main** toolbar. If the **Show this dialog at next startup** check box is selected, the **Scan Network** dialog box will open automatically each time DeviceLock Enterprise Manager is started.

There are three simple steps, which enable you to manage DeviceLock Services across the network.

### **Selecting Computers**

The first step is to select the computers to be processed.

You can use the context menu, available by right clicking, to select/deselect necessary items (computers types, domains, or computers).

DeviceLock Enterprise Manager provides several flexible ways to select network computers.

• Network computers can be selected by their types.

Each type represents all of the computers belonging to the category:

- Primary Domain Controller a primary domain controller.
- Backup Domain Controller a backup domain controller.
- Microsoft SQL Servers any server running with Microsoft SQL Server.

- **Terminal Servers** any server where Terminal Services are running.
- **Stand Alone Servers** any server that is not a domain controller.
- **Cluster Servers** server clusters available in the domain.
- **Print Servers** any computer that is sharing the print queue.
- **NT Workstations** any Windows NT/2000/XP workstation.

There are two ways to choose the type of computers:

1. **Types** – you select the network domain and then select types of computers which must be processed in this domain.

Select domain(s) and computer's type(s)	
Types 💌	
	4

2. **Domains** – you select the type of computer and then select network domains where computers of the selected type must be processed.

Select computer's type(s) and domain(s)
Domains

• Network computers can also be selected by their names.

There are several ways to choose computers by name:

1. **Organizational Units** – you browse Active Directory organizational units (OUs) and select computers, which must be processed.

Select computer(s) from OUs	
Organizational Units	•
Computers     Computers     Developers     Omain Controllers     AMDSALES     Maragers     MMX2000     P4NATALI     P4VIT     P2VIT     Servers     Test OU     testing	

2. **Computers** – you browse the network tree and select computers.



3. **LDAP** – you browse the LDAP (Lightweight Directory Access Protocol) tree and select computers from the directory.

Select computer(s) from the LDAP Tree	
LDAP	144
🗊 💼 Users	
Stest	
E B testing	
E-100 testlab2K	
VMXPPROFSP2	
Uomain Controllers	

To configure a connection to the LDAP server, click the ... button.

LDAP Sett	ings ? 🔀
Host:	192.168.100.25
Port:	389 Protocol version: 3
Base DN:	cn=qa,o=SMARTLINE,c=US
User DN:	cn=admin,o=SMARTLINE,c=US
Password:	•••••
	OK Cancel

**Host** – the name or the IP address of the LDAP server to connect to. **Port** – the TCP port on which the LDAP server accepts connections. The default port is 389.

**Protocol version** – the LDAP protocol version. Some servers are not fully compatible with the LDAP v.3 protocol and LDAP requests require certain adjustments for correct communication with such servers. Selecting **Version 2** makes sure that the server requests are adjusted according to the LDAP v.2 protocol requirements.

**Base DN** – the starting point for you to browse the directory tree. You must use the LDAP string representation for distinguished names (for example, cn=qa,o=SMARTLINE,c=US). Leave the **Base DN** box blank to start browsing from the root.

By clicking the **Fetch** button, you can get all the published naming contexts. **User DN** – the distinguished name (DN) of the directory user that allows connection to the directory. You must use the LDAP string representation for distinguished names (for example, cn=admin,o=SMARTLINE,c=US). **Password** – the user's password.

4. **From File** – you load a predefined list of computers from the external text file and then select the computers.

To open an external file, click the ... button.



A text file must contain each computer's name or IP address on separate lines and can be either Unicode or non-Unicode. A brief example of such a file follows:

Computers.txt - Notepad	
pro sl_server sl_server3 sl_server2 pili600 fujitsu_laptop acer_laptop terminal4	X
<u> </u>	► ///

#### **Supplying Credentials**

If you need to supply alternative credentials for the target computer(s), select the computer or network domain from the tree and point to **Credentials** on the context menu.

Select comp	uter(s) from the file	Seje	ect Plug-in
From File			🖻 Audit Log Vie
	)MAIN> PRO Select		Install service Report Permis Report PnP D Set Permission
	Deselect		🔞 Uninstall servi
	Select All		
0	Deselect All		
	Refresh	F5	
	Credentials		🔒 Set
	Set Port		🗙 Clear

You may assign credentials to individual computers and/or to network domains. To add credentials, click **Set**. To delete alternative credentials, click **Clear**.

Credentials consist of a user name and password pair used to authenticate the computers processed. By default, DeviceLock Enterprise Manager uses your currently logged on credentials to automatically log in and process the target computer(s). If the current logged-in user credentials do not have administrative rights on all of the target computers, you need to enter alternate credentials. DeviceLock Enterprise Manager will use these alternate credentials to automatically login to the target computers.

In all cases, credentials are stored with encryption techniques and are not available to anyone except the user with administrative privileges.

Enter the userna permission to the	me and password for an account with adminis specified computer/domain.	trative
Username:	administrator	
Password:	********	
⊻erify	*******	
When specifying domainname\use	a domain account, use the format rname	
	OK	Cancel

Credentials can also be supplied via the **Credentials** dialog box. To open the **Credentials** dialog box, click **Credentials** on the **File** menu.

🛠 Credentials		<u>?×</u>
Domain\Computer	User Name	Add
SPVIRT	admin	Change
MI2000SERVER	test	Changen
E FUJITSU_LAPTOP	administrator	Delete
		Close

Click **Add** to add new credentials. To change existing credentials, select the record in the list and click **Change**.

To delete credentials, select the record in the list and click **Delete**. Using CTRL and/or SHIFT you can select and remove several records simultaneously.

#### **Setting Port**

You can instruct DeviceLock Enterprise Manager to use a fixed port, making it easier to configure a firewall. To do so, use **Set Port** from the context menu.

Select computer(s) Computers	Seject Plug-in
Microsoft Win     SL     SL	dows Report P Select Deselect Select All Deselect All
	Refresh F5 Refresh Current Domain Ctrl+F5 Credentials
og at next startup	Set Port

By default, DeviceLock Enterprise Manager uses dynamic ports for RPC communication with DeviceLock Service. However, if DeviceLock Service is configured to accept connections on a fixed port, select the **Specify port** option.

Set Port for PRO	?×
O Dynamic ports	
Specify port:	1245
	OK Cancel

To use the dynamic ports binding, click **Dynamic ports**.

DeviceLock Service can be configured to use either a fixed port or dynamic ports during the installation process. For more information on this, see "<u>Unattended Installation</u>" and "<u>Remote Installation via DeviceLock Enterprise Manager</u>."

If you need to change the port configuration when DeviceLock Service is already installed, use the <u>Install service</u> plug-in.

For information on which ports are required for which actions, see "Plug-ins."

#### **Selecting Plug-ins**

The second step is to select a plug-in to process the network computers selected on the first step.

To select/deselect plug-ins, you can use the context menu available with a right mouse click.



To define parameters for the selected plug-in, use the **Settings** button below the plug-ins list. If the plug-in does not have additional parameters, this button is unavailable.

Tasks are passed to the plug-in by DeviceLock Enterprise Manager.

The plug-in performs the task and returns the information to DeviceLock Enterprise Manager. Upon receipt of a plug-in's information, DeviceLock Enterprise Manager displays it in a separate window.

#### Starting a Scan

Once you have selected computers and the appropriate plug-in, the final step is starting the scan process. Click **Scan** to initiate the process.

Right after the scan process is initiated, you can start to explore the information that is already received from the plug-in.

Because the scan process runs in a separate thread, you do not need to wait until all computers are finished being scanned. You can also perform other tasks in the DeviceLock Enterprise Manager interface.

There are only a few things which you cannot do while the scan is running – you cannot close DeviceLock Enterprise Manager and you cannot run another scan process.

If, for some reason, you wish to abort the active scan process, you can click **Stop Scan** on the **File** menu or press the appropriate button on the **Main** toolbar. The scan process will be aborted as soon as a plug-in returns control to DeviceLock Enterprise Manager.



## **Plug-ins**

DeviceLock Enterprise Manager has a flexible plug-in based architecture that allows you to plug in the necessary module on demand. DeviceLock Enterprise Manager loads the plug-ins on startup from the **Plugins** subdirectory, which is located in the main DeviceLock Enterprise Manager directory.

DeviceLock Enterprise Manager ships with standard plug-ins that require some network ports to be opened on remote computers, as described in the table below:

REQUIRED PORTS	PLUG-INS AFFECTED
<b>TCP 139 or TCP 445</b> <b>UDP 137</b> – this port must be opened only when a connection is established by the computer name. If an IP address is used, this port is not required.	<u>Audit Log Viewer, Report</u> <u>PnP Devices</u>
<b>TCP 139 or TCP 445</b> <b>UDP 137</b> – this port must be opened only when a connection is established by the computer name. If an IP address is used, this port is not required.	<u>Install Service</u> , <u>Uninstall</u> <u>Service</u>
TCP 139 or TCP 445 TCP 135 – this port is required only when the Dynamic ports connection is used. TCP <all 1024="" above="" ports=""> – these ports are required only when the Dynamic ports connection is used.</all>	<u>Report</u> <u>Permissions/Auditing</u> , <u>Set</u> <u>Service Settings, Shadow</u> <u>Log Viewer</u>
<ul> <li>TCP <custom port=""> – this port is required only when the Fixed port connection is used.</custom></li> <li>UDP 137 – this port must be opened only when a connection is established by computer name. If an IP address is used, this port is not required.</li> </ul>	

For information on how to use either the **Dynamic ports** or **Fixed port** connection in DeviceLock Enterprise Manager, see "<u>Setting Port</u>."

When a plug-in is connected to a remote computer it may receive some of these error messages:

- The product version on the client and server machines does not match (7049) – you are trying to connect to a computer where an old version of DeviceLock Service is installed. You should upgrade DeviceLock Service first using the <u>Install Service</u> plug-in.
- The network path was not found (53) you are trying to connect to a computer that either does not exist (the wrong name or IP address) or is not accessible. Make sure that the computer name you have specified is correct. Try to access this computer with Windows Explorer and connect to it using any standard Windows administrative tool (such as Computer Management, Services and so on).

This error also occurs when the standard Windows Server service is not running on the remote computer. Check the Server service status and start it if it is stopped.

More connection errors are described in the <u>Possible Connection Errors</u> section of this manual.

### **Audit Log Viewer**

The Audit Log Viewer plug-in retrieves DeviceLock's audit log from the computer's local Windows event logging subsystem.

To define a maximum log size and what Windows should do if the audit log becomes full, use **Audit Log Settings** from the context menu.

To clear all events from the audit log, select **Clear Audit Log** from the context menu.

For more information, see "Audit Log Viewer (Service)."

### **Install Service**

The Install Service plug-in installs or updates DeviceLock Service on computers.

Before you can use this plug-in, you should specify the directory that contains all of the files needed for installation (such as DeviceLock Service.msi, DeviceLock Service x64.msi, DLRemoteInstaller.exe, and InstMsiW.exe). You can do this by clicking the **Settings** button below the plug-ins list in the **Scan Network** dialog box (see "<u>Selecting Plug-ins</u>").

For more information, see "Remote Installation via DeviceLock Enterprise Manager."

### **Report Permissions/Auditing**

The Report Permissions/Auditing plug-in generates a report that allows you to view and change security policies defined for device types and protocols across the network.

Before you can use this plug-in, you should select the information you want to include in the report. You can do this by clicking the **Settings** button below the plug-ins list in the **Scan Network** dialog box (see "<u>Selecting Plug-ins</u>").

📲 Report Permissions	2
Devices         Report Available Devices Only         Device type(s)         V BlackBerry       V Infrared port         V Dipboard       V Panallel port         V Clipboard       V Parallel port         V FireWire port       V Printer         V Floppy       V Removable         V Hard disk       Serial port	Protocols      Report Protocols      Protocol type(s)      V FTP     V Telnet     Web Mail      V CQ/AOL Messenger     V Malows Messenger     V Jabober      Mal.ru Agent     V Social Networks
Report Auditing & Shadowing     Preport Enabled Auditing & Shadowing Only     Report Security Settings     Report Content-Aware Rules     Report USB White List     Report Media White List	Report Auditing & Shadowing     Preport Enabled Auditing & Shadowing Only     Report Security Settings     Report Content-Aware Rules     Report Protocols White List
Report DeviceLock Administrators	
	OK Close

In the **Report Permissions** dialog box, specify the information that you want to include in your report.

To receive information on the security policies defined for device types, under **Devices**, use the following options:

- Report Available Devices Only select this check box to report permissions and audit rules for only those devices currently available on the computer. Otherwise, you will see permissions and audit rules for every type of device that DeviceLock supports.
- Report Auditing & Shadowing select this check box to report audit and shadowing rules that have been set. Also when this check box is selected, you receive information about whether the Log Policy changes and Start/Stop events parameter is enabled in <u>Service Options</u>.
- **Report Enabled Auditing & Shadowing Only** select this check box to exclude devices for which audit and shadowing rules are disabled from the report. *This option is available only if the Report Auditing & Shadowing check box is selected.*
- Report Security Settings select this check box to report what parameters are disabled via <u>Security Settings</u>.
- **Report Content-Aware Rules** select this check box to report Content-Aware Rules that have been set (see "<u>Content-Aware Rules for Devices</u>").
- Report USB White List select this check box to include information about white listed devices (see "USB Devices White List").
- Report Media White List select this check box to include information about white listed media (see "Media White List").
- **Report DeviceLock Administrators** select this check box to report accounts that can manage DeviceLock Service or view its settings and logs.

To receive information on the security policies defined for protocols, under **Protocols**, use the following options:

• **Report Protocols** – select this check box to report security policies for protocols. Otherwise, information on all protocol-based policies will be excluded from the report.

*If the Report Protocols check box is cleared, the Report Auditing & Shadowing option and the Report Enabled Auditing & Shadowing Only option are unavailable.* 

- **Report Auditing & Shadowing** select this check box to report audit and shadowing rules that have been set for protocols.
- **Report Enabled Auditing & Shadowing Only** select this check box to exclude protocols for which audit and shadowing rules are disabled from the report. *This option is available only if the Report Auditing & Shadowing check box is selected.*
- Report Security Settings select this check box to report what parameters are defined via <u>Security Settings</u>.
- Report Content-Aware Rules select this check box to report Content-Aware Rules that have been set for protocols (see <u>Content-Aware Rules for Protocols</u>").
- Report Protocols White List select this check box to include information about white listed protocols (see "Managing Protocols White List").

This report always includes information about an installed <u>DeviceLock Certificate</u>. Also, it always shows when the **Use Group Policy** parameter is enabled in <u>Service Options</u>.

### **Report PnP Devices**

The Report PnP Devices plug-in generates a report displaying the USB, FireWire and PCMCIA devices currently connected to computers on the network and those that were connected.

**Note:** In order to retrieve PnP devices from Windows Vista/7 and Windows Server 2008 computers, you should allow remote access to the PnP interface on those computers. You can do it via modifying the policy as described in this article: <a href="mailto:support.microsoft.com/kb/947040">support.microsoft.com/kb/947040</a>.

The columns are defined as follows:

- **Description** the description of the device provided by its vendor.
- **Device Information** the additional information about the device provided by its vendor.
- Connected to the interface where the device is connected (USB, FireWire or PCMCIA).
- **Class** the class of the device provided by Windows.
- **Class description** the description of the device's class provided by Windows.
- **Present** indicates whether the device is currently connected or not (**Yes** or **No**).

- **DeviceID** the unique identification string of the device provided by its vendor.
- **Driver** the name of the driver that is controlling this device.

You can add reported USB devices to the <u>USB Devices Database</u> using the context menu available via a right mouse click.

Before you can use this plug-in, you should select the information you want to include in reports. You can do this by clicking the **Settings** button below the plug-ins list in the **Scan Network** dialog box (see "<u>Selecting Plug-ins</u>").



- **Report Connected Devices Only** select this check box to report only those devices that are currently connected to the computer. Otherwise, you will see all devices that were ever connected to the computer.
- **Report FireWire Devices** select this check box to report devices that are plugging into the FireWire port.
- **Report PCMCIA Devices** select this check box to report devices that are plugging into the PCMCIA slot.
- Report USB Devices select this check box to report devices that are plugging into the USB port.

#### **Set Service Settings**

The Set Service Setting plug-in reads the policy (settings, permissions, audit and shadowing rules) from the external XML file and deploys it to DeviceLock Services across the network.

**Note:** Only settings that are explicitly defined in a policy file apply to client computers. All policy settings that have the **Not Configured** state are ignored by client computers.

Before you can use this plug-in, you should define settings, permissions and/or audit rules that you want to deploy. You can do this by clicking the **Settings** button below the plug-ins list in the **Scan Network** dialog box (see "<u>Selecting Plug-ins</u>").

ame	Cre	ated	Modified	Author
🛛 🗊 DL Set	tings 1 6/2	0/2007 8:06:45 PM	6/20/2007 8:06:52 PM	VM2000AD\Administrator
📑 DL Set	tings 2 7/10	0/2007 12:16:05 PM	6/20/2007 8:06:52 PM	VM2000AD\Administrator
] 🍠 Main D	L Settings 7/10	0/2007 12:16:14 PM	6/20/2007 8:06:52 PM	VM2000AD\Administrator
New	Add	Edit		

First of all you have to prepare the policy you want to deploy.

If there are no files in the list, then you can either create an empty file by clicking the **New** button or add an existing file by clicking the **Add** button.

Then select the file in the list and click **Edit** to open DeviceLock Service Settings Editor. DeviceLock Service Settings Editor is used for creating and modifying external XML files with settings, permissions, audit and shadowing rules for DeviceLock Service. For more information, see "<u>DeviceLock Service Settings Editor</u>."

When finished modifying the policy, select its file by selecting the check box next to the file's name in the list. Then click **OK** to close the configuration dialog box.

### **Shadow Log Viewer**

The Shadow Log Viewer plug-in retrieves the shadow log from DeviceLock Service.

Use the context menu available by a right mouse click to access all this plug-in's functions.

For more information, see "Shadow Log Viewer (Service)."

### **Uninstall Service**

The Uninstall Service plug-in removes DeviceLock Service and all its settings and components from computers.

If the user under which DeviceLock Enterprise Manager is connecting to the computer does not have full administrative access to DeviceLock Service, the plug-in will not be able to remove the service. Likewise, an error occurs when the user does not have local administrative privileges on the computer where DeviceLock Service is running.

# **Open / Save / Export**

DeviceLock Enterprise Manager can store all information received from plug-ins.

The data is saved to external files and is ready for loading into DeviceLock Enterprise Manager when requested.

There are three ways to save and load data:

1. The handiest method to store received information is to save it as a project. When you are saving data as a project, DeviceLock Enterprise Manager saves each active plug-in's window to a separate file of its own format and places this file in the **Project** subdirectory.

The names of the project's files are auto-generated and depend on the plug-in's names and the date and time when the scan was started.

To save the data as a project, you can select **Save Project** from the **File** menu or press the appropriate button on the **Main** toolbar.

🔋 Open Project			
Project A	Project	:t Type	
E Audit Log Viewer			
👪 7/15/2006 12:04:31 AM	Scang	result	L,
🛱 🖽 Report Permissions/Auditing		Open project(s)	1
	Scan	Crown by Physics	
E Report PnP Devices		Group by Plug-Ins	
	Scan	Group by Date	
🖻 🚯 Shadow Log Viewer		E Compare	
- 👸 7/15/2006 1:33:15 AM	Scan		_
- 👸 7/19/2006 12:35:11 AM	Scan	Tr Filter	
- 👸 7/22/2006 12:56:41 AM	Scan	-	-
- 👸 7/22/2006 1:05:18 AM	Scan	Refresh	
- 👸 7/22/2006 1:25:18 AM	Scan	View Mode	
- 😽 7/25/2006 12:31:59 AM	Scan	view mode	<u> </u>
	_	Enable Grid	
		X Delete project(s)	

To load previously saved projects, select **Open Project** from the **File** menu.

The **Open Project** window has its own toolbar and context menu available by a right mouse click.

You can group saved projects by the date when they were scanned and by the type of information they contain. Select **Group by Plug-ins** or **Group by Date** from the context menu or press appropriate buttons on the **Project** toolbar.

To open a saved project, select it from the list and press the **Open Project** button on the **Project** toolbar. Using CTRL and/or SHIFT, you can select and open several projects simultaneously.  Another way to save received information in the format of DeviceLock Enterprise Manager is select **Save As** from the **File** menu. This enables you to save a file of the ANM type to any place on your hard disk or any other media with any name you choose.

To load previously saved files, you can select **Open** from the **File** menu or press the appropriate button on the **Main** toolbar. You will need to specify a file you wish to open. You can load files of the ANM type only.

3. If you need to pass received information to a third-party application, you can export it into an external file and then import it to this application. To export data into the external file, select Save As from the File menu and then select the file's type from the Save as type box. DeviceLock Enterprise Manager supports the export into MS Excel (if it is installed on the local computer) and two formats of text files – Tab Delimited (TXT) and Comma Delimited (CSV).

If you export information into an external file, you will not be able to load it back to DeviceLock Enterprise Manager because DeviceLock Enterprise Manager can open and load only files of its own format. However, the ability to export into an external file is useful when you wish to exchange data between DeviceLock Enterprise Manager and other applications.

# **Comparing Data**

DeviceLock Enterprise Manager allows you to track changes on network computers by comparing two previously saved projects. Tracking changes is important when managing a wide range of computers on one network.

DeviceLock Enterprise Manager provides a very useful and intuitive Wizard to compare two ANM files. To open this Wizard, select **Compare** from the **File** menu.

There are three simple steps, which enable you to compare two files using the Compare Wizard:

1. The first step is to select the files you want to compare.

Туре	Report Permissions/Auditing
Date	01.02.05 16:15:03
C:\Pro	rme gram Files\DeviceLock\Projects\Report Permissions_Auditing - [0]
Tupe	Report Permissions / Auditing
туре	incourt emissions/walking
Date	02.04.05 21:11:04

Select the first file and then select the second file by using the ellipsis (...) buttons.

Please note that you can compare files of the same type only. For example, you cannot compare information received from the Report Permissions/Auditing plug-in with information from the Report PnP Devices plug-in.

When you have selected two files, press the **Next** button to go to the Wizard's next page.

2. The second step is to select the columns you wish to include in the compare process.

Select Columns To Compare	×
Select Columns To Compare	Included columns
Ignore domains I Show char < <u>B</u> ack	nges only Finish Cancel Help
DeviceLock Enterprise Manager compares only those columns, which you have selected. If you need to exclude one column from the compare process, you have to move it from the **Included columns** list to the **Excluded columns** list. Excluded columns will be visible in the compare result, but the values they contain are ignored and do not affect the compare result.

By default, the compare result contains only records, which are different in the two files being compared. If you would like to see all of the records (even unchanged records), you can clear the **Show changes only** check box.

To include names of the network domains in the compare process, you can clear the **Ignore domains** check box. When the **Ignore domains** check box is selected, DeviceLock Enterprise Manager ignores domains and only compares computers and the information those computers contain.

3. The third and final step is to start the compare process. Press the **Finish** button to compare two selected files with each other.

DeviceLock Enterprise Manager displays the compare result in a separate window in the form of a tree exactly as it displays information received from a plug-in.



The comparison is very simple and effective:

1. If the **Ignore domains** check box is cleared, the program enumerates network domains in the two selected files and tries to find each domain in both the older file and the recent file.

If the domain exists in the older file but does not exist in the recent file, DeviceLock Enterprise Manager inserts the missing domain (along with all the computers contained in that domain as well as the information in those computers) into the comparison result and then writes all those records in red.

If the domain does not exist in the older file but exists in the recent file, DeviceLock Enterprise Manager inserts the missing domain (along with all the computers contained in that domain as well as the information in those computers) into the comparison result and then writes all those records in green.

If the domain exists in both files, DeviceLock Enterprise Manager enumerates all the computers the domain contains (see below).

2. If the **Ignore domains** check box is selected, DeviceLock Enterprise Manager ignores domains and enumerates all the computers in the two selected files and tries to find each computer in both older and recent files.

If the computer exists in the older file but does not exist in the recent file, DeviceLock Enterprise Manager inserts the missing computer with all information it contains into the compare result and writes all these records in red.

If the computer does not exist in the older file but exists in the recent file, DeviceLock Enterprise Manager inserts the missing computer with all information it contains into the compare result and writes all these records in green.

If the computer exists in both files, DeviceLock Enterprise Manager enumerates all the information it contains (see below).

3. DeviceLock Enterprise Manager enumerates all information for a computer and tries to find each record in both the older and the recent file.

If the record exists in the older file but does not exist in the recent file, DeviceLock Enterprise Manager inserts the missing record into the compare result and writes it in red.

If the record does not exist in the older file but exists in the recent file, DeviceLock Enterprise Manager inserts the missing record into the compare result and writes it in green.

If the record exists in both files, DeviceLock Enterprise Manager starts comparing each included column for this record:

 If the column's values for the older and the recent files are different, DeviceLock Enterprise Manager inserts both records in the compare result. The record from the recent file comes right after the record from the older one.

The column that belongs to an older record is highlighted in red. The column that belongs to a recent record is highlighted in green. All excluded columns and columns with equal values are not highlighted and are written in the default color.

• If all of a record's columns for both files contain equal values, DeviceLock Enterprise Manager either skips this record (the **Show changes only** check box is selected) or inserts this record into the compare result and writes it in the default color (the **Show changes only** check box is cleared). If you wish to compare two files, which were saved as projects, it is a good idea to use the special feature of the **Open Project** window.

Select **Open Project** from the **File** menu, select two projects you would like to compare (use CTRL and/or SHIFT to select two projects simultaneously) and then select **Compare** from the context menu or press the appropriate button on the **Project** toolbar.

# *Please note that you may select only two projects and both projects must be of the same type.*





DeviceLock Enterprise Manager provides two buttons on the **Compare** toolbar, which help you to easily navigate through the compare result. Press the < button to select the previous record in the compare result that contains changes. Press the > button to select the next record in the compare result that contains

changes.

You can also save the compare result to an external ANM file or export it into MS Excel or the text file (TXT and CSV). Select **Save As** from the **File** menu or press the appropriate button on the **Main** toolbar to save or export the compare result.

Main Toolbar	×
2 5 🕞 🖬 🗐 🛓	Ă↑

As with any other DeviceLock Enterprise Manager file, the saved compare result can be opened and loaded to DeviceLock Enterprise Manager. To load the previously saved compare result, you can select **Open** from the **File** menu or press the appropriate button on the **Main** Toolbar. You will need to specify a file you want to open. You can load files of ANM type only.

# **Filtering Data**

DeviceLock Enterprise Manager provides very sophisticated data filtering, enabling you to narrow a scan or comparison result to only those data complying to your specific conditions.



To open the **Filter Data** dialog box, you can select **Filter** from the **View** menu or press the appropriate button on the **Main** toolbar.

Field	Condition	Value	Value	Apply
Description	Not defined			
Device Information	Not defined			Cancel
Connected To	Not defined			
Class	Not defined			
Class Description	Not defined			
Present	Is (exactly)	Yes		
DeviceID	Not defined			
Driver	Not defined			
				-
				-
				-
d				4

**Note:** The window with a scan or comparison result must be active to use data filtering.

• The **Field** column contains all the fields available in the scan or comparison result that you want to filter. You can define the **AND-OR** logic for each field separately:

**AND** – includes only those records that comply with all defined conditions. For example, Process = "explorer.exe" AND PID = 3764 retrieves all data where both the Process is "explorer.exe" and PID is 3764. It does not include data where the Process is "explorer.exe" and PID is not 3764 or where PID is 3764 but Process is not "explorer.exe".

**OR** – includes all records that comply with at least one condition. For example, Process = "explorer.exe" OR PID = 3764 retrieves all data having one or both conditions, where Process = "explorer.exe" (no matter what PID is) or where PID is 3764 (no matter what Process is).

• The **Condition** column contains a list of logical operations that can be performed on a selected field. You can select only one logical operation for each field. DeviceLock Enterprise Manager supports two groups of logical operations, those for string data and non-string data.

Logical operations that can be performed on string data (target string being the string you specify, for example, "Explorer.exe"):

- **Is (exactly)** selects only data having fields with strings that are identical to the target string.
- **Includes** selects only data having fields with strings that include a defined target string.
- **Is not** selects only data having fields with strings that are different from the target string.

- Not includes selects only data having fields with strings that do not include the target string.
- **Empty** selects only data having fields with empty strings.
- **Not Empty** selects only data having fields with strings that are not empty.
- Regular expression selects only data having fields with strings matching an expression. The expression may contain wildcards (for example, "explorer\*").

If you want to narrow the search to the string's exact case (for example, "Explorer.exe" is different from "explorer.exe"), select the **Match case (for string data)** check box. Otherwise, case is ignored (for example, "Explorer.exe" and "explorer.exe" are identical).

Logical operations that can be performed on non-string data:

- Equal to (=) selects data having field values that are identical to the defined value (for example, PID = 3764).
- **Greater than (>)** selects data having field values that are greater than the defined value (for example, PID > 4).
- Less than (<) selects data having field values that are less than the defined value (for example, PID < 4).
- Not Equal to (!=) selects data having field values that are different from the defined value (for example, PID != 0).
- **Between (in)** selects data having field values that are between the two defined values (for example, PID in 3000-4000).
- Not Between (out) selects data having field values that are outside of the two defined values (for example, PID out 3000-4000).
- **Regular expression** selects only data having field values matching an expression. The expression may contain wildcards (for example, 300\*).

If you do not want to perform a logical operation for a field, select **Not defined** from the list of logical operations.

• Value columns contain user-defined arguments. The second Value column is used only when the **Between (in)** or **Not Between (out)** logical operation is selected. For all other logical operations only the first Value column is needed.

After you define a filtering expression, press the **Apply** button to start the filtering process.

You can save a filtered result in an external ANM file or export it to a text file (TXT and CSV) or MS Excel. select **Save As** from the **File** menu or press the



appropriate button on the **Main** toolbar to save or export the filtered result.

As with any other DeviceLock Enterprise Manager file, filtered data can be opened and loaded into DeviceLock Enterprise Manager. To load a file, select **Open** from the **File** menu or press the appropriate button on the **Main** toolbar. Then specify the file you want to open. You can only load files that were previously saved by DeviceLock Enterprise Manager.

# **Content-Aware Rules for Devices (Regular Profile)**

Content-Aware Rules extend the basic port/device access control functionality of DeviceLock by adding comprehensive, file-level protection of corporate documents containing confidential company information. Content-Aware Rules enable automatic content inspection of data copied to external storage devices, detection of sensitive content and enforcement of regulatory policies to ensure protection.

With Content-Aware Rules, you can selectively allow or deny access to specific file content regardless of preset permissions at the device type-level. You can also use Content-Aware Rules to allow or deny shadow copying of specific content. For flexibility, Content-Aware Rules can be defined on a per-user or per-group basis.

You can configure Content-Aware Rules to apply to access control operations, to shadow copy operations, or both.

The following examples illustrate the use of Content-Aware Rules.

- Example 1 Using Content-Aware Rules for access control operations. You can allow certain users or groups to read files containing the phrase "not for distribution" from Removable, Floppy, and CD/DVD devices but prevent them from writing files containing more than one credit card number to Removable and Floppy devices.
- Example 2 Using Content-Aware Rules for shadow copy operations. You can specify that only files containing credit card numbers, Social Security numbers, the words "Secret", "Confidential", "Restricted," and the phrases "Top Secret", and "For Official Use Only" will be shadow copied for security auditing and incident investigation purposes.

**Note:** You can define different online vs. offline Content-Aware Rules for the same user or sets of users. Online Content-Aware Rules (Regular Profile) apply to client computers that are working online. Offline Content-Aware Rules (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define offline Content-Aware Rules, see "Managing Offline Content-Aware Rules for Devices."

# **Content-Aware Rules for Access Control Operations**

When Content-Aware Rules apply to access control operations, they control read, write and delete operations for specified content. Delete and write operations are controlled together.

Content-Aware Rules allow you to do the following:

- Grant read/write access to specified file content when access is denied at the device type-level.
- Deny read/write access to specified file content when access is granted at the device type-level.

**Note:** DeviceLock can check access to devices at two levels: the interface (port) level and the type level. Some devices are checked at both levels, while others only at one level – either interface (port) or type. For example, a USB flash drive belongs to both levels: interface (USB) and type (Removable). Content-Aware Rules work only when access checking occurs at the type level (Removable, Floppy, etc.). DeviceLock does not perform the access check for USB devices at the type level if the following conditions are true:

- the device is not added to the USB Devices White List, **Access control for USB storage devices** is enabled in **Security Settings** and the user has no access to the **USB port** device type. OR

- the device is added to the USB Devices White List and the **Control As Type** check box is cleared for it.

ACCESS RIGHTS	DESCRIPTION
Generic: Read	Controls whether the user can read specified content from a device. Applies to the DVD/CD-ROM, Floppy, and Removable device types.
Generic: Write	Controls whether the user can write specified content to a device. Applies to the Floppy and Removable device types.
Generic: Read, Write	Controls whether the user can read and write specified content from and to a device. Applies to the Floppy and Removable device types.
Encrypted: Read	Controls whether the user can read specified content from an encrypted device. Applies only to the Removable device type.
Encrypted: Write	Controls whether the user can write specified content to an encrypted device. Applies only to the Removable device type.
Encrypted: Read, Write	Controls whether the user can read and write specified content from and to an encrypted device. Applies only to the Removable device type.

The following table provides summary information on access rights that can be specified in Content-Aware Rules.

**Note:** Generic access rights specified for the Removable device type apply only to unencrypted devices. Encrypted access rights specified for the Removable device type apply only to encrypted devices. To specify access rights for both encrypted and unencrypted Removable devices, you must specify both Generic and Encrypted access rights. For detailed information on devices that are recognized by DeviceLock Service as encrypted devices, see "Encryption."

The following table shows how different device type-level and file-level permissions affect the state of a permission for a user account. Device type-level permissions are permissions set for a device type. File-level permissions are permissions defined by Content-Aware Rules.

## Content-Aware Rules for Devices (Regular Profile)

	FULL ACCESS device type-level	NO ACCESS device type-level	ALLOW READ/ DENY WRITE device type-level
ALLOW READ file-level	allows read access to all content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies read access to all but specified content, denies creation and renaming of empty folders and zero byte (0) files.	allows read access to all content, denies creation, deletion, and renaming of empty folders and zero byte (0) files.
<b>DENY READ</b> file-level	denies read access to specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies access to a device	denies read access to specified content, denies creation, deletion, and renaming of empty folders and zero byte (0) files.
ALLOW WRITE file-level	allows write access to all content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies write access to all but specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies write access to all but specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.
<b>DENY WRITE</b> file-level	denies write access to specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies access to a device	denies write access to all content, denies creation, deletion, and renaming of empty folders and zero byte (0) files.
ALLOW READ/ ALLOW WRITE file level	allows read and write access to all content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies read and write access to all but specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	allows read access to all content, denies write access to all but specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.
DENY READ/ DENY WRITE file-level	denies read and write access to specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies access to a device	denies read access to specified content, denies write access to all content, denies creation, deletion, and renaming of empty folders and zero byte (0) files.
ALLOW READ/ DENY WRITE file-level	allows read access to all content, denies write access to specified content, allows creation,	denies read access to all but specified content, denies write access to all content, denies creation and	allows read access to all content, denies write access to all content, denies creation, deletion, and renaming

#### Content-Aware Rules for Devices (Regular Profile)

	FULL ACCESS device type-level	NO ACCESS device type-level	ALLOW READ/ DENY WRITE device type-level
	deletion, and renaming of empty folders and zero byte (0) files.	renaming of emty folders and zero byte (0) files.	of empty folders and zero byte (0) files.
DENY READ/ ALLOW WRITE file-level	denies read access to specified content, allows write access to all content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies read access to all content, denies write access to all but specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.	denies read access to specified content, denies write access to all but specified content, allows creation, deletion, and renaming of empty folders and zero byte (0) files.

**Note:** If the No Access permission is set for a device type and there is a Content-Aware Rule that allows write access to certain content for the same device type, the Traverse Folder permission is granted to users for this device type. The Traverse Folder permission allows the user to move through folders and see files and folders located in subdirectories even if the user has no Read permission for the traversed folders.

When using Content-Aware Rules, consider the following:

- If Content-Aware Rules are defined for both devices and protocols, all access checks are executed in one thread.
- Content-Aware Rules with Deny settings take priority over rules with Allow settings if they apply to the same users or groups.
- When users try to overwrite an existing file with a new file to which they are denied write access, the old file is deleted.
- When users try to modify a file to which they are denied write access, the file is deleted.
- Unsafe removal of a device can result in the corruption of the device's file system and data.
- When users try to copy files to which they are denied write access, these files are temporarily visible in Windows Explorer or other file manager applications. Actually, these files do not really exist on the target device, they are located in the memory cache and are removed from this cache immediately after DeviceLock finishes checking their content.
- When users open a file from the USB flash drive, modify it by inserting the content to which they are denied write access and then try to save changes, the file is deleted.
- Checking the content of files can be a time-consuming operation. You cannot safely remove the device while this operation is in progress even if the copied files become visible in Windows Explorer or other file manager

applications. In this situation, you receive an error message indicating that the device is currently busy.

- Newly copied files cannot be opened for reading until DeviceLock finishes checking their content.
- Checking the content of files can be a time-consuming operation. You can define a Content verification message to be displayed to users when content inspection is in progress. For detailed information on this message, see "Content verification message" in "Service Options".
- When users try to read or write files to which they are denied read or write access, they receive a DeviceLock Content-Aware blocked read or write message, if Content-Aware blocked read or write message is enabled in Service Options. For detailed information on these messages, see "Content-Aware blocked read message" and "Content-Aware blocked write message" in "Service Options."

# **Content-Aware Rules for Shadow Copy Operations**

Before you can use Content-Aware Rules for shadow copy operations, you must turn on shadowing in **Auditing and Shadowing** at the device type-level. Content-Aware Rules that apply to shadow copy operations filter the shadow copies of files written by the user.

The following table provides summary information on shadowing rights that can be specified in Content-Aware Rules.

SHADOWING RIGHTS	DESCRIPTION
Generic: Write	Controls whether or not specified content written to a device is shadow copied. Applies to the Floppy, iPhone, Removable, Palm, and Windows Mobile device types.
Generic: Print	Controls whether or not documents with specified content sent to printers are shadow copied. Applies to the Printer device type.
	DeviceLock extracts and analyzes text from PostScript, PCL5, and PCL6 files.
Encrypted: Write	Controls whether or not specified content written to an encrypted device is shadow copied. Applies only to the Removable device type.
Special Permissions: Write Calendar	Controls whether or not specified content written to a calendar on a mobile device from a PC is shadow copied. Applies to the iPhone, Palm, and Windows Mobile device types.
Special Permissions: Write Contact	Controls whether or not contacts with specified content written from a PC to a mobile device are shadow copied. Applies to the iPhone, Palm, and Windows Mobile device types.
Special Permissions: Write E-mail	Controls whether or not e-mail messages with specified content written from a PC to a mobile device are shadow copied. Applies to the iPhone, Palm, and Windows Mobile device types. For iPhone, this right controls shadow copying of e-mail account settings but not e-mail messages

SHADOWING RIGHTS	DESCRIPTION
	because iTunes does not support sync of messages.
Special Permissions: Write Attachment	Controls whether or not e-mail attachments with specified content written from a PC to a Windows Mobile or Palm device are shadow copied.
Special Permissions: Write Favorite	Controls whether or not favorites with specified content written from a PC to a Windows Mobile device or iPhone are shadow copied.
Special Permissions: Write File	Controls whether or not files with specified content written from a PC to a mobile device are shadow copied. Applies to the iPhone, Palm, and Windows Mobile device types.
Special Permissions: Write Media	Controls whether or not media data with specified content written using Windows Media Player to a Windows Mobile device from a PC and media files with specified content written to a Palm device and iPhone from a PC are shadow copied.
Special Permissions: Write Backup	Controls whether or not the iPhone backup data with specified content written from a PC to iPhone is shadow copied.
Special Permissions: Write Note	Controls whether or not notes with specified content written from a PC to a mobile device are shadow copied. Applies to the iPhone, Palm, and Windows Mobile device types.
Special Permissions: Write Pocket Access	Controls whether or not Pocket Access databases with specified content written from a PC to a Windows Mobile device are shadow copied.
Special Permissions: Write Task	Controls whether or not tasks with specified content written from a PC to a mobile device are shadow copied. Applies to the Palm and Windows Mobile device types.
Special Permissions: Write Expense	Controls whether or not Palm Expense application data with specified content written from a PC to a Palm device is shadow copied.
Special Permissions: Write Document	Controls whether or not Palm documents with specified content written from a PC to a Palm device are shadow copied.
Special Permissions: Write Unidentified Content	Controls whether or not any other uncategorized data with specified content written from a PC to a Windows Mobile device is shadow copied.

**Note:** Generic shadowing rights specified for the Removable device type apply only to unencrypted devices. Encrypted shadowing rights specified for the Removable device type apply only to encrypted devices. To specify shadowing rights for both encrypted and unencrypted Removable devices, you must specify both Generic and Encrypted shadowing rights.

# **Configuring Content Detection Settings**

Content-Aware Rules are created based on content groups that enable you to centrally define types of content for which you want to control access. Content groups specify content filtering criteria that will be used to select data to which rules should be applied.

All content groups are stored in the Content Database. The same Content Database is used for both devices and protocols. The Content Database is a part of the DeviceLock Service policy and is also saved in an XML file with service settings that can be created using DeviceLock Management Console, DeviceLock Service Settings Editor, and DeviceLock Group Policy Manager.

There are several types of content groups: File Type Detection groups, Keywords groups, Pattern groups, Document Properties groups, and Complex groups. The sections below describe these groups and how to use them.

# **File Type Detection Content Groups**

File Type Detection groups are used to control access to files based on file types. These groups contain definitions of the file types that make up these groups. A file type definition consists of two properties: a file name extension (for example, DOC) and a description (for example, Microsoft Word document). When you apply a rule based on a File Type Detection group, the rule is applied to all file types included in that group.

By defining rules based on File Type Detection groups, you can, for example, allow certain users or groups to read Word documents from Floppy devices but prevent them from writing Word documents to Floppy devices. You can deny read access to all executable files from Removable, DVD/CD – ROM and Floppy devices but allow write access to all file types for Removable and Floppy devices. You can also specify that only Word, Excel, and PDF documents will be shadow copied.

DeviceLock includes 34 predefined (built-in) File Type Detection groups that you can use to set up the desired configuration of permissions and/or shadow copy operations. You can use the built-in content groups as they are, create their editable copies (duplicates) or create your own content groups to suit your particular organization's needs.

The following table lists these predefined content groups:

Archives Audio, Video & Flash BlackBerry Common Object File Format (COFF) Database Executable Fax Documents FileMaker Pro Fonts Help Files Images, CAD & Drawing Lotus SmartSuite	MS Outlook & Outlook Express MS PowerPoint MS Project MS Publisher MS Visio MS Windows Installer MS Windows Memory Dump MS Word MS Word MS Works OpenOffice, StarOffice, OpenDocument, etc. PDF, PostScript, & XPS Documents QuickBooks, Quicken, TurboTax & etc.
MS Access	Rich Text Format
MS Excel	Security Certificates
MS InfoPath	Text, HTML & XML
MS Money	Virtual Machines

## **BUILT-IN FILE TYPE DETECTION GROUPS**

#### **BUILT-IN FILE TYPE DETECTION GROUPS**

MS OneNote	WordPerfect Office

**Note:** Content-Aware Rules support Word To Go, Sheet To Go, and Slideshow To Go formats for Palm devices. Word To Go format is included in the MS Word and Rich Text Format built-in content groups, Sheet To Go format is included in the MS Excel built-in content group, while Slideshow To Go format is included in the MS PowerPoint built-in content group.

Microsoft Word or Rich Text Format (RTF) files, Excel files and PowerPoint files can be transferred to a Palm device using the Documents To Go application. The Documents To Go application converts these files to special formats: Word and RTF files are converted to Word To Go format, Excel files are converted to Sheet To Go format, while PowerPoint files are converted to Slideshow To Go format. The converted files are automatically downloaded to the Palm when users synchronize.

With built-in content groups, you can quickly create and apply rules without having to define your own content groups.

**Note:** You can view file type definitions that are included in the built-in File Type Detection groups but you cannot edit or delete them. For information on how to view the built-in content groups, see "<u>Viewing Built-in Content Groups</u>."

## **Creating Custom File Type Detection Groups**

You can define Content-Aware Rules based on your own (custom) content groups if the predefined content groups included with DeviceLock do not meet your requirements. Custom File Type Detection content groups enable you to specify any file types that you want in the same group to better meet your individual business needs.

For example, suppose you need to grant certain users access to Word, Excel, PDF documents and graphic files. To do this, first you create a new File Type Detection content group that represents these document content types. Then you define a rule based on this custom content group.

#### To create a custom File Type Detection group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.

- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

M Content-Aware Rules						? 🛛
Content Database						
Description					Typ	pe 🔺
ABA Routing Number					Pat	tern (bi
Acquisition					Key	words (
Admission Discharge					Key	words (
American Address					Key	words (
American Name					Key	words (
Archives					File	Type D
Audio, Video & Flash					File	Type D 🗸
<u>د</u>						2
Add Test Group Duplic	ate Add Group 👻	Edit Group	Delete Group	Show: All	Types	*
Users A	Rules Description Typ	xe Ac	tion(s)	Applies To	Protocol(s)	
Add Delete	Delete Edt	] -			Load	Save
				OK	Cancel	Apply

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **File Type Detection**.

The Add File Type Detection Group dialog box appears.

Content Group		Available Content	
Extension Description		Find Find	Previous Filter
		Extension	Description
	<		2Calc data yEnc Encoded XNA Game Studio resource HP Xine compressed X cursor Xbox: 360 PIRS container data file Xbox: 360 ILVE container data file Xbox: 360 CON container data file Works 4.0 for Macintosh WIDDEV data (generic) WDDEV
		<	>

- 5. In the left pane of the **Add File Type Detection Group** dialog box, under **Content group**, type the name of the new content group in the **Name** box.
- 6. In the right pane of the **Add File Type Detection Group** dialog box, under **Available Content**, select any file type you want to add to the new content group, and then click the left single-arrow button

You can select multiple file types by holding down the SHIFT key or the CTRL key while clicking them.

To remove single file types from the content group, use the right single-arrow button  $\square$ . To add or remove all available file types to or from the content group at the same time, use the left double-arrow button  $\square$  or right double-arrow button  $\square$ .

**Note:** You can search the available content database for specific file types by extension or description. You can use wildcards such as asterisks (\*) and question marks (?) to search for a specific group of file types. To find a specific file type or specific group of file types, under **Available Content**, type an extension or description with or without wildcards in the search string, and then click **Find**. To filter file types, click **Filter**. To remove the filter, apply it to an empty string.

An asterisk (\*) replaces an unlimited number of characters. The question mark (?) replaces a single character. You can use these wildcards in any position and in any quantity.

7. Click **OK** to close the **Add File Type Detection Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

# **Keywords Content Groups**

Keywords groups are used to control access to files based on whether certain words or phrases occur in a document.

By defining rules based on Keywords groups, you can, for example, allow read access to all documents containing the phrases "Top Secret" and "For Official Use Only" from Removable, Floppy and DVD/CD–ROM devices but deny write access to Removable and Floppy devices for these documents. You can also specify that only documents containing the phrases "Top Secret" and "For Official Use Only" will be shadow copied.

DeviceLock includes 157 predefined (built-in) Keywords groups that you can use to set up the desired configuration of permissions and/or shadow copy operations. You can use the built-in content groups as they are, create their editable copies (duplicates) or create your own content groups to suit your particular organization's needs.

The following table lists these predefined content groups:

#### **BUILT-IN KEYWORDS GROUPS**

Accounting Documentation Terms Accounting Documentation Types Acquisition Active substance Admission Discharge Adult Keywords American Address American Name Bank ABA Bank ACNT Bank STMT Board Meeting Breach of Obligation Breach of Standards Breach of the Law Business Documentation Business Documentation Terms Business Documentation Types Business Rivals	Production Charges Profanity Profiles Profit Loss Project Names Project Release Dates Property Racism Keywords Resume Russian: Account Statement Russian: Accounting Documentation Russian: Accounting Documentation Terms Russian: Accounting Documentation Types Russian: Bank Account Russian: Bank Account Russian: Bank Operations Russian: Banking Operations Participants Russian: Breach of Commitment Russian: Breach of Law Russian: Business Documentation
Business Trips & Meetings	Russian: Business Documentation Terms
C# Source Code	Russian: Business Documentation Types
Collular Operator Call Log	Russian: Business Faithers
COBOL Source Code	Russian: Company Development Plan
CODOL Source Code	Russian: Company Development Fian Russian: Companyation and Benefits
Common Medical Terms	Russian: Confidential Information
Company Development	Russian: Corporate Capital
Compensation and Benefits	Russian: Corporate Property
Compliance Report	Russian: Expenses
Confidential	Russian: Failures
Confidential Partners Information	Russian: Financial Information
Credit Report	Russian: Financial Report
Credits	Russian: Financial Terms
Discontent	Russian: Firing
Discrediting Information	Russian: Innovations
Driver's License	Russian: Insurance
Employer Identification Number	Russian: Internal Payments
Ethnicity	Russian: Investors and Investments
Executive Job Searches	Russian: Labor Law

Failures	Russian: Loans and Credits
Financial Report	Russian: Manufacturing
Financial Statements	Russian: Market Development Plan
Firing	Russian: Medicinal Active Substances
FITS Date & Time	Russian: Medicinal Drugs
FITS File Checksum	Russian: Noncompliant
FITS File Descriptors	Russian: Passwords and Access Codes
FITS Hierarchical file grouping	Russian: Physical Security
FITS Instrumentorum	Russian: Prices
FITS Non-standard	Russian: Project Documentation
FITS Observations	Russian: Project Names
FITS Standard	Russian: Project Versions
Gambling	Russian: Projects Release Date
Grades	Russian: Technology
HCFA (CMS) 1500 Form	Russian: User Names
HIPAA - Diseases	Russian: Working Conditions
HIPAA HCPCS	Sales Forecast
HIPAA ICD9	Sarbanes-Oxley Sensitive
HIPAA NDC Classes	Security
HIPAA NDC Dosages	Security Agencies
HIPAA NDC Listing	Sensitive Disease
HIPAA NDC Routes	Sexual Language
Illegal Drugs	Social Security
Innovations	SPAM
Internet Slang Abbreviations	Sports
Investments	Staff Training
Java Source Code	Substance Abuse
Market Development	Suspicious Activity Report
Medical Diagnosis	Technology
Medical Record Numbers	UBO4 Form
MEMO	US Birth Date
Network Security	US Birth Place
Partner Names	US Expiry Date
Password	User Name
Payments	VB Source Code
PCI GLBA	Violence
Peri Source Code	weapon keywords
Price List	Wire Transfer
Prices	Working Conditions
Pro Earnings	

With built-in content groups, you can quickly create and apply rules without having to define your own content groups.

**Note:** You can view keywords that are included in the built-in Keywords groups but you cannot edit or delete them. For information on how to view the built-in content groups, see "<u>Viewing Built-in Content</u> <u>Groups</u>."

## **Creating Custom Keywords Groups**

You can define Content-Aware Rules based on your own (custom) content groups if the predefined content groups included with DeviceLock do not meet your requirements. Custom Keywords content groups enable you to specify any keywords that you want in the same group to better meet your individual business needs.

### To create a custom Keywords group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

Content-Aware Rules		2 🛛
Content Database		
Description		Туре 🔥
R ABA Routing Number		Pattern (b.
Acquisition		Keywords (
Admission Discharge		Keywords (
American Address		Keywords (
American Name		Keywords (
Archives		File Type D
R Audio, Video & Flash		File Type D 🐱
<		>
Add Test Group Dup	cate Add Group   Edit Group Delete Group Show:	All Types 🗸
Users A	Description Type Action(s) Applies	To Protocol(s)
Add Delete	Delete Edit	Load Save
	OK	Cancel Apply

 In the upper pane of the Content-Aware Rules dialog box, under Content Database, click the drop-down arrow next to Add Group, and then click Keywords.

The Add Keywords Group dialog box appears.

5		
ame:		
escription:		
Condition:	Match any keyword(s)	Threshold: 1
Keyword	is	Case Sensitive Whole Word
Add	Delete	Load

5. In the **Add Keywords Group** dialog box, do the following:

USE THIS	TO DO THIS				
Name	Specify the name of the group.				
Description:	Specify a description for the group.				
Condition:	<ul> <li>Specify conditions for firing rules associated with this content group. To do so, in the <b>Condition</b> list, click any of the following options: <ul> <li>Match any keyword(s) indicates that a rule associated with this content group is activated every time any of the specified keywords is found within text data.</li> <li>Match all keyword(s) indicates that a rule associated with this content group is activated every time all of the specified keywords are found within text data.</li> <li>Only when combined score exceeds (or equal to) threshold indicates that a rule associated with this content group is activated every time the total number (sum) of occurrences of all found keywords within text data equals or exceeds the threshold number of occurrences of the keywords.</li> </ul> </li> </ul>				
Threshold	Specify the threshold number of occurrences of the keywords. This number can range from 0 to 65535. This property requires a value if you selected the <b>Only when combined score exceeds (or equal to) threshold</b> option.				
Keywords	Specify words and phrases that must occur within text data. Double- click under <b>Keywords</b> to enter a keyword or phrase.				
Case Sensitive	Determine the case sensitivity of the keywords. Select the <b>Case</b> <b>Sensitive</b> check box to specify a case-sensitive comparison of the keywords (for example, the words "test" and "Test" will be treated as different keywords.). Clear the <b>Case Sensitive</b> check box to specify a case-insensitive comparison of the keywords (for example, the words "test" and "Test" will be treated as the same keyword).				
Whole Word	Specify keyword matching options. Select the <b>Whole Word</b> check box to specify the exact match option (allows you to find an exact match of your keyword). Clear the <b>Whole Word</b> check box to specify the broad				

USE THIS	TO DO THIS
	match option (allows you to find all grammatical variations of your keyword).
Weight	Specify the degree of importance for each keyword or phrase. Weight is used to count the number of occurrences of the specified keywords within text data. This property requires a value if you selected the <b>Only when combined score exceeds (or equal to) threshold</b> option.
	Possible values: Heavy, Above Normal, Normal (default value), Below Normal, Light.
	These weight values are interpreted as follows:
	<b>Heavy</b> weight indicates that each keyword occurrence is counted as three occurrences. This value is the highest.
	<b>Above Normal</b> weight indicates that each keyword occurrence is counted as two occurrences.
	<b>Normal</b> weight indicates that each keyword occurrence is counted as one occurrence.
	<b>Below Normal</b> weight indicates that two keyword occurrences are counted as one occurrence.
	<b>Light</b> weight indicates that three keyword occurrences are counted as one occurrence. This value is the lowest.
Add	Specify keywords and phrases. Click <b>Add</b> to enter a keyword or phrase.
Delete	Delete a keyword. To do so, select the keyword you want to delete, and then click <b>Delete</b> . You can select multiple keywords by holding down the SHIFT key or the CTRL key while clicking them.
Load	Import a list of keywords from a tab-delimited text file.

#### 6. Click **OK** to close the **Add Keywords Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

# **Pattern Content Groups**

Pattern groups let you control access to text files using patterns of text described by Perl regular expressions. Patterns provide a flexible and powerful way to automatically detect potentially sensitive content (for example, credit card numbers, Social Security numbers, e-mail addresses, and phone numbers) within documents.

For more information on creating and using Perl regular expressions, refer to the <u>Perl</u> regular expressions guick start tutorial and <u>Perl regular expressions tutorial</u>.

By defining rules based on Pattern groups, you can, for example, prevent certain users or groups from writing documents containing credit card numbers to Removable and Floppy

devices. You can also turn off shadow copying of documents that do not contain credit card numbers.

DeviceLock includes 45 predefined (built-in) Pattern groups that you can use to set up the desired configuration of permissions and/or shadow copy operations. You can use the built-in content groups as they are, create their editable copies (duplicates) or create your own content groups to suit your particular organization's needs.

The following table lists these predefined content groups:

### **BUILT-IN PATTERN GROUPS**

With built-in content groups, you can quickly create and apply rules without having to define your own content groups.

**Note:** You can view regular expression patterns that are included in the built-in Pattern content groups but you cannot edit or delete them. For information on how to view the built-in content groups, see "<u>Viewing Built-in Content Groups</u>."

# **Creating Custom Pattern Groups**

You can define Content-Aware Rules based on your own (custom) content groups if the predefined content groups included with DeviceLock do not meet your requirements. Custom content groups enable you to specify any pattern that you want to use to identify sensitive information within documents.

#### To create a custom Pattern group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

Content-Aware Rules		2 🛛
Content Database		
Description		Туре 🔥
R ABA Routing Number		Pattern (b.
Acquisition		Keywords (
Admission Discharge		Keywords (
American Address		Keywords (
American Name		Keywords (
Archives		File Type D
R Audio, Video & Flash		File Type D 🐱
<		>
Add Test Group Dup	cate Add Group   Edit Group Delete Group Show:	All Types 🗸
Users A	Description Type Action(s) Applies	To Protocol(s)
Add Delete	Delete Edit	Load Save
	OK	Cancel Apply

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Pattern**.

The Add Pattern Group dialog box appears.

Add Pat	tern Group	? 🛛
Name:		
Description:		
Expression:		Validate
Validation:	No Validation	~
Condition:	Greater than 🔽 1	Advanced >>
Test sample:		
	1	OK Cancel

5. In the **Add Pattern Group** dialog box, do the following:

USE THIS	TO DO THIS
Name	Specify the name of the group.
Description:	Specify a description for the group.
Expression	Specify a pattern by creating a regular expression. For information on how to create Perl regular expressions, refer to the <u>Perl regular</u> expressions quick start tutorial and <u>Perl regular expressions tutorial</u> .
Validate	Check regular expression syntax.
Validation	Perform the actual validation on the potential matches returned by the regular expression. The following options are available: <b>No validation</b> (this option is selected by default), <b>ABA Routing Number</b> , <b>Canadian</b> <b>Social Insurance Number</b> , <b>Credit Card Number (All)</b> , <b>Credit Card</b> <b>Number (American Express)</b> , <b>Credit Card Number (Diners</b> <b>Club)</b> , <b>Credit Card Number (Diners Club En Route)</b> , <b>Credit Card</b> <b>Number (Discover)</b> , <b>Credit Card Number (JCB)</b> , <b>Credit Card</b> <b>Number (Laser)</b> , <b>Credit Card Number (Maestro)</b> , <b>Credit Card</b> <b>Number (Master Card)</b> , <b>Credit Card Number (Solo)</b> , <b>Credit Card</b> <b>Number (Switch)</b> , <b>Credit Card Number (Visa)</b> , <b>Credit Card</b> <b>Number (Visa Electron)</b> , <b>Date, Date (ISO)</b> , <b>Email Address</b> , <b>European VAT Number, IBAN</b> , <b>IP Address</b> , <b>LUHN Checksum</b> , <b>Russian Bank Account Number</b> , <b>Russian Health Insurance</b> <b>Number</b> , <b>Russian Taxpayer Identification Number</b> , <b>Russian</b> <b>Main State Registration Number</b> , <b>Russian Classification Of</b> <b>Enterprises And Organizations</b> , <b>UK National Insurance Number</b> , <b>UK Phone Number</b> , <b>UK Post Code</b> , <b>UK Tax Code</b> , <b>URL</b> , <b>US Social</b> <b>Security Number</b> .
Condition:	Specify conditions for firing rules associated with this content group. To do so, in the <b>Condition</b> list, click any of the following options:
	• Less than or = indicates that a rule associated with this content group is activated every time the number of matches returned by the regular expression is less than or equal to the specified number.
	Equal to indicates that a rule associated with this content

USE THIS	TO DO THIS
	group is activated every time the number of matches returned by the regular expression is equal to the specified number.
	<ul> <li>Greater than or = indicates that a rule associated with this content group is activated every time the number of matches returned by the regular expression is greater than or equal to the specified number.</li> </ul>
	<ul> <li>Between indicates that a rule associated with this content group is activated every time the number of matches returned by the regular expression is within the specified range.</li> </ul>
Advanced	Quickly test your regular expression pattern on sample data. Click <b>Advanced</b> to display or hide the <b>Test sample</b> box.
Test sample	Enter a test string and view the result. DeviceLock supports real-time color highlighting of test results. All matches are highlighted in green, while strings that do not match the pattern are highlighted in red.

6. Click **OK** to close the **Add Pattern Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

# **Document Properties Content Groups**

Document Properties groups are used to control access to files based on file properties such as file name, size, etc. You can also use a Document Properties content group to control access to password-protected documents and archives as well as text images.

**Note:** The AND logic is applied to all file properties specified within a Document Properties group. For example, if you want to control access to files larger than 5 megabyte (MB) in size and password-protected documents and archives, you should create two separate Document Properties groups: one group for files larger than 5 MB in size and another group for password-protected documents and archives. If you specify these file properties within the same Document Properties group and then create a Content-Aware Rule based on this content group, this rule will control password-protected documents and archives that are larger than 5 MB.

By defining rules based on Document Properties groups, you can, for example, allow read access to all documents larger than 1 MB in size from Removable, Floppy and DVD/CD – ROM devices but deny write access to Removable and Floppy devices for these documents. You can also specify that only documents whose size exceeds 5 MB will be shadow copied.

There are no predefined (built-in) Document Properties content groups to use. The following procedure describes how to create your own Document Properties group.

## To create a Document Properties group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

Content-Aware Rules						? 🛛
Content Database						
Description					Туре	^
ABA Routing Number					Pattern (	ы
Acquisition					Keyword	s (
Adult Keywords					Keyword	51
American Address					Keyword	5(
American Name					Keyword	s (
Archives					File Type	D
Audio, video ornash					rie type	
			16.0			
Add Test Group Duplice	Add	sroup I*	roup Delete Group	Show: All Typ	es	~
Content-Aware Rules						
Users	Rules					
Users 🔺	Description	Туре	Action(s)	Applies To	Protocol(s)	
Add Delete	Delete	Edit			Load Save	- 11
				OK	Cancel Ap	ply

 In the upper pane of the Content-Aware Rules dialog box, under Content Database, click the drop-down arrow next to Add Group, and then click Document Properties.

The Add Document Properties Group dialog box appears.

lame:	1				
escription:					
Properties					
File name:					~
Modified:	Not specified	• 07 /26/2	010 03:57 AM 🛃	07 /26/2010 03:57	AM 🔽
File size:	Not specified	• 0	0	bytes	×
Passwor	protected				
Text ext	action not suppor	ted			
Contains	text 0	<u></u> %			
Accessed by	process:				~

5. In the Add Document Properties Group dialog box, do the following:

USE THIS	TO DO THIS
Name	Specify the name of the group.
Description:	Specify a description for the group.
File name	Specify the file names. You can use wildcards, such as asterisks (*) and question marks (?). For example, type <b>*.txt</b> to specify all files that have the .txt extension. Multiple file names must be separated by a semicolon (;), for example, <b>*.doc; *.docx</b> .
	An asterisk (*) replaces an unlimited number of characters. The question mark (?) replaces a single character.
	<b>Note:</b> For shadowing data captured from the Printer device type, the file name value you specify is compared with names provided in the <b>File Name</b> column of the Shadow Log Viewer.
Modified	Specify the last modification date/time of the file. To do so, in the <b>Modified</b> list, click any of the following options:
	Not specified (this option is selected by default)
	• <b>Before than</b> indicates that the file's modified date/time must be earlier than the specified date/time.
	<ul> <li>After than indicates that the file's modified date/time must be later than the specified date/time.</li> </ul>
	• <b>Between</b> indicates that the file's modified date/time must fall within the specified date/time range.
	<ul> <li>Not older than indicates that the file's modified date/time must not be older than the specified number of seconds, minutes, days, weeks, months, and years.</li> </ul>
	• <b>Older than</b> indicates that the file's modified date/time must be older than the specified number of seconds, minutes, days,

USE THIS	TO DO THIS
	weeks, months, and years.
File size	<ul> <li>Specify the file size in bytes, kilobytes, megabytes, gigabytes or terabytes. To do so, in the File size list, click any of the following options:</li> <li>Not specified (this option is selected by default)</li> <li>Equal to indicates that the file(s) must have a size that is equal to the size you specify.</li> <li>Less than indicates that the file(s) must have a size that is less than the size you specify.</li> <li>More than indicates that the file(s) must have a size that is more than the size you specify.</li> <li>Between indicates that the file size must fall within the specified range.</li> </ul>
Password protected	Detect and control access to password-protected archives, PDF files, and Microsoft Office documents (.doc, .xls, .ppt, .docx, .xlsx, .pptx). If you select the <b>Password protected</b> check box for a Document Properties group and then create a Content-Aware Rule based on this content group, this rule will control access to password-protected archives, PDF files, and Microsoft Office documents. Clear the <b>Password protected</b> check box if you do not want to detect and control access to password-protected archives, PDF files, and Microsoft Office documents. For information on the supported archive formats, see the description of the "Inspection of files within archives" feature.
Text extraction not supported	Control access to unsupported file formats. If you select the <b>Text</b> <b>extraction not supported</b> check box for a Document Properties group and then create a Content-Aware Rule based on this content group, this rule will control access to all files in an unsupported format. All supported file formats are listed in the " <u>Extending DeviceLock</u> <u>Functionality with ContentLock and NetworkLock</u> " section.
Contains text	Detect and control access to images based on whether or not they contain text. If you select the <b>Contains text</b> check box for a Document Properties group and then create a complex Content-Aware Rule based on this content group and the built-in Images, CAD & Drawing content group (File Type Detection) combined by the AND operator, this rule will check whether supported image files contain text and control access to text images. Clear the <b>Contains text</b> check box if you do not want to detect and control access to text images. For information on the supported image files, see the description of the " <u>Text in picture detection</u> " feature. If you select the <b>Contains text</b> check box, specify the amount of text that images must contain. The amount of text is expressed as a percentage of the total image area. For example, if text occupies ½ of
	<ul> <li>he image is the total image dreat for example, in text occupies 72 of the image, the amount of text makes 50%. If an image contains only text, the amount of text is 100%.</li> <li>Note: The Contains text % option also applies to other supported file formats. In this case, the percentage means the ratio of the text size in characters to file size in bytes.</li> </ul>

USE THIS	TO DO THIS
Accessed by process	Specify the name of the process accessing the document's file. You can use wildcards, such as asterisks (*) and question marks (?). Multiple process names must be separated by a semicolon (;), for example, <b>explorer.exe; notepad.exe</b> .

6. Click **OK** to close the **Add Document Properties Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

# **Complex Content Groups**

Complex groups use Boolean expressions to select documents for which you want to control access. These groups can include any combination of built-in or custom content groups (File Type Detection, Keywords, Pattern, and Document Properties groups) linked with any number of the standard logical operators. Each content group is treated as a single filter criterion that can be included in your Boolean expression. By using multiple content groups, you can create complex filters to identify sensitive content contained in documents.

OPERATOR	MEANING
NOT	Logical negation of a filter criterion
AND	Both filter criteria must apply
OR	Either filter criterion can apply

The following table lists the logical operators in order of precedence from highest to lowest.

You can use parentheses to modify the precedence of operators and force some parts of an expression to be evaluated before others. Nested criteria enclosed in parentheses are evaluated in inner-to-outer order. Multiple levels of nesting are supported. A complex group can contain a maximum of 30 content groups.

There are no predefined (built-in) Complex content groups to use. The following procedure describes how to create your own Complex group.

#### To create a Complex group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

Content-Aware Rules		
Content Database		
Description		Туре 🐣
ABA Routing Number		Pattern (b.
Acquisition		Keywords (
Admission Discharge		Keywords (
Adult Keywords		Keywords (
American Address		Keywords (
American Name		Keywords (
Audio, Video & Flash		File Type D 🗸
<		2
Add Test Group Dus	licate Add Group 💌 Edit Group Del	lete Group Show: All Types
Users A	Pules Description Type Action	(s) Applies To Protocol(s)
Add Delete	Delete Edit	Load
		OK Cancel Apply

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Complex**. The Add Complex Group dialog box appears.

🔍 Add Complex Group		2 🛛
Name: 1		
Description:		
Add Insert View Delete		A V
NOT (	Criteria	) AND/OR
Result		(M)
		<u>M</u>
Clear Validate		OK Cancel

5. In the **Add Complex Group** dialog box, do the following:

USE THIS	TO DO THIS
Name	Specify the name of the group.
Description:	Specify a description for the group.
Add	Add the desired content groups from the Content Database. To do so, click <b>Add</b> to open the <b>Content Groups</b> dialog box. In the <b>Content Groups</b> dialog box, under <b>Content Database</b> , select the desired content group, and then click <b>OK</b> .
	You can select multiple content groups by holding down the SHIFT key or the CTRL key while clicking them.
	<i>To view information about a content group, select the desired group, and then click View Group.</i>
	The content groups you added appear in the Criteria column in the Add Complex group dialog box. Each content group you add is treated as a single filter criterion that can be included in your Boolean expression.
Insert	Insert a content group from the Content Database before the currently selected group in the <b>Criteria</b> column. To do so, click <b>Insert</b> to open the <b>Content Groups</b> dialog box. In the <b>Content Groups</b> dialog box, under <b>Content Database</b> , select the desired content group, and then click <b>OK</b> .
View	View information about the currently selected group in the <b>Criteria</b> column.
Delete	Delete the selected group from the <b>Criteria</b> column.
NOT	Join each content group you select with the logical NOT operator. To do so, select the desired group in the <b>Criteria</b> column, and then select

USE THIS	TO DO THIS
	the appropriate check box in the <b>Not</b> column.
AND/OR	Join each content group you select with the logical AND or OR operator. To do so, select the desired group in the <b>Criteria</b> column, and then click either <b>AND</b> or <b>OR</b> in the appropriate list in the <b>AND/OR</b> column.
Clear	Clear the current list of content groups in the <b>Criteria</b> column.
Validate	Validate your expression. If the expression was defined incorrectly (for example, an opening parenthesis was not matched with a closing parenthesis), you receive an error message.

6. Click **OK** to close the **Add Complex Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

# **Viewing Built-in Content groups**

You can view any built-in content groups but you cannot edit or delete them.

#### To view a built-in content group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any built-in group you want to view, and then click **View Group**.

# **Duplicating Built-in Content groups**

You cannot edit the built-in content groups but you can create and use their editable copies (duplicates) to suit your particular organization's needs.

#### To duplicate a built-in content group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

- 4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any built-in group you want to duplicate, and then click **Duplicate**.
- 5. In the dialog box that opens, edit the content group as required, and then click **OK**.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

# **Editing and Deleting Custom Content Groups**

You can modify or delete custom content groups at any time.

### To edit or delete a custom content group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

- 4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any custom group you want to edit or delete.
- 5. Click **Edit Group** to modify the selected content group. In the dialog box that opens, make the required changes, and then click **OK**.

- OR -

Click **Delete Group** or press the DELETE key to delete the selected content group.

6. In the **Content-Aware Rules** dialog box, click **OK** or **Apply** to apply the changes.

# **Testing Content Groups**

You can test any built-in or custom content group to see whether specified files match with it. By using these tests, you can verify that the rules that are created based on the content groups meet your specific business requirements.

#### To test a content group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any content group you want to test, and then click **Test Group**.

You can test only one group at a time.

The Open dialog box appears.

- 5. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to use for testing the specified content group.
- 6. In the folder list, locate and open the folder that contains the file.
- 7. Click the file, and then click **Open**.

The Result message box is displayed. If the file matches with the specified content group, the Result message box contains the following text: "Selected file matches with the group." If the file does not match with the specified content group, the Result message box contains the following text: "Selected file does not match with the group."

When testing is in progress, the console stops responding (hangs)

# **Managing Content-Aware Rules**

Managing Content-Aware Rules involves the following tasks:

- Defining Content-Aware Rules
- Editing Content-Aware Rules
- Copying Content-Aware Rules
- Exporting and importing Content-Aware Rules
- Undefining Content-Aware Rules
- Deleting Content-Aware Rules

You can manage Content-Aware Rules using DeviceLock Management Console, DeviceLock Group Policy Manager, or DeviceLock Service Settings Editor.

# **Defining Content-Aware Rules**

Content-Aware Rules are created based on either the built-in or custom content groups. For detailed information on these groups, see "<u>Configuring Content Detection Settings</u>."

#### To define a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

Content-Aware Rules			?
Content Database			
Description			Туре 🖌
ABA Routing Number			Pattern (b.
R Acquisition			Keywords (
Admission Discharge			Keywords (
Adult Keywords			Keywords (
American Address			Keywords (
American Name			Keywords (
Audio Video & Flach			File Type D
C Made, Theo or hash			
Add Test Group D	uplicate Add Group 💌 Edit Group	Delete Group Show:	All Types
Users	Rules		
Users A	Description Type	Action(s) Applies	To Protocol(s)
Add Delete	Delete Edit		Load Save

4. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

5. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups for which you want to define the rule, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules dialog box.

To delete a user or group, in the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group, and then click **Delete** or press the DELETE key.

6. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the users or groups for which you want to define the rule.

*You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.* 

7. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select the desired content group, and then click **Add**.

**Note:** You can specify only one content group for a Content-Aware Rule.

The Add Rule dialog box appears.

Add Rule	2
Description: Credit Card I	Number
Applies to	
Permissions Shado	wing
Devices Type(s):	
Actions	
Actions User's Rights	Allow Deny

8. In the **Add Rule** dialog box, in the **Description** box, type the name of the Content-Aware Rule.

By default, the Content-Aware Rule has the same name as the specified content group but you can enter a different name.

- 9. Under **Applies to**, specify the type of operation associated with the rule. The available options are:
  - **Permissions**: Specifies that the rule will apply to access control operations.
  - **Shadowing**: Specifies that the rule will apply to shadow copy operations.
  - **Permissions**, **Shadowing**: Specifies that the rule will apply to both access control and shadow copy operations.
- 10. Under **Device Type(s)**, select the appropriate device type(s) you would like this rule to be applied to.

*Content-Aware Rules can be applied to the DVD/CD-ROM, Floppy, iPhone, Palm, Removable, and Windows Mobile device types.* 

If you select several device types that have different access rights, under Action(s), the dialog box displays only those access rights that are common to all selected device types.
11. Under **Action(s)**, specify which user actions are allowed or disallowed on files and which user actions are logged to the shadow log.

You can select any of the following options: Read, Write, Read and Write.

If the rule applies to shadow copy operations or both access control and shadow copy operations, the Read option becomes unavailable. For detailed information on user rights that can be specified in Content-Aware Rules, see "<u>Content-Aware Rules for Access Control Operations</u>" and "<u>Content-Aware Rules for Shadow Copy</u> <u>Operations</u>."

12. Click **OK**.

*The rule you created is displayed under Rules in the lower-right pane of the Content-Aware Rules dialog box.* 

13. Click **OK** or **Apply** to apply the rule.

The users or groups to which the Content-Aware Rule applies are displayed under Content-Aware Rules in the console tree. When you select a user or group to which a Content-Aware Rule applies in the console tree, in the details pane you can view detailed information regarding this rule. This information includes the following:

- **Description** The name of the rule. By default, the rule has the same name as the specified content group.
- Type The type of the content analysis. Possible values: File Type Detection, Keywords, Pattern, Document Properties, and Complex. File Type Detection indicates that recognition and identification of files is based on their characteristic signatures. Keywords indicates that recognition and identification of data/files is based on the specified keywords or phrases.
   Pattern indicates that recognition and identification of data/files is based on the specified patterns of text described by Perl regular expressions.
   Document Properties indicates that recognition and identification of files is based on their properties. Complex indicates that recognition and identification of data/files is based on the specified content described by a Boolean expression.
- Action(s) Shows which user actions are allowed or disallowed on files and which user actions are logged to the Shadow Log.
- Applies To Possible values: Permissions, Shadowing, and Permissions, Shadowing. Permissions indicates that the rule applies to access control operations. Shadowing indicates that the rule applies to shadow copy operations. Permissions, Shadowing indicates that the rule applies to both access control and shadow copy operations.
- **Device Type(s)** The device type(s) to which the rule applies.
- **Profile** Possible values: **Regular** and **Offline**. **Regular** indicates that the rule applies to client computers that are working online. **Offline** indicates that the rule applies to computers that are working offline.

You can define different online vs. offline Content-Aware Rules for the same user or sets of users. For information about how to define offline Content-Aware Rules, see "<u>Managing Offline Content-Aware Rules for Devices</u>."

## **Editing Content-Aware Rules**

You can modify the Content-Aware Rule properties such as Description, Applies To, Device Type(s), Actions.

#### To edit a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, right-click **Content-Aware Rules**, click **Manage**, and then do the following:
  - a) In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group for which you want to edit the rule. By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.
  - b) In the lower-right pane of the Content-Aware Rules dialog box, under Rules, select the rule you want to edit, and then click Edit.
     OR -

Right-click the rule, and then click **Edit**.

- Under Devices, expand Content-Aware Rules, and then do the following:
  - a) Under **Content-Aware Rules**, select the user or group for which you want to edit the rule.

*By selecting users or groups, you can view the Content-Aware Rules applied to them in the details pane.* 

b) In the details pane, right-click the rule you want to edit, and then click Edit.
 - OR -

In the details pane, double-click the rule you want to edit.

The Edit Rule dialog box appears.

- 4. In the **Edit Rule** dialog box, modify the rule properties as required to meet your needs.
- 5. Click **OK** to apply the changes.

<sup>-</sup> OR -

## **Copying Content-Aware Rules**

You can perform a cut-and-paste operation, a copy-and-paste operation or a drag-and-drop operation to reuse existing Content-Aware Rules.

#### To copy a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

4. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group to which the rule that you want to copy is applied.

*By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.* 

5. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, right-click the rule you want to copy, and then click **Copy** or **Cut**.

The rule you cut or copy is automatically copied to the Clipboard.

You can use the CTRL+C, CTRL+X and CTRL+V key combinations to copy, cut and paste the rule. When you use the CTRL+X key combination to cut the rule, the rule will be cut only after you paste it.

To perform a drag-and-drop operation, select the rule and move it to the user or group to which you want to apply the copied rule.

6. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

7. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups to which you want to apply the copied rule, and then click **OK**. The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules dialog box.

8. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the users or groups to which you want to apply the copied rule.

*You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.* 

9. In the lower-right pane of the **Content-Aware Rules** dialog box, right-click in the **Rules** pane and then click **Paste**.

The copied rule is displayed under Rules in the lower-right pane of the Content-Aware Rules dialog box.

10. Click **OK** or **Apply** to apply the copied rule.

## **Exporting and Importing Content-Aware Rules**

You can export all your current Content-Aware Rules to a .cwl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

#### **To export Content-Aware Rules**

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Save.
     OR -
  - Select Content-Aware Rules, and then click Save 

     OR
  - Expand **Content-Aware Rules**, right-click any user or group to which the rule is applied, and then click **Save**.
    - OR -
  - Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Save**.

- OR -

- Expand Content-Aware Rules, select any user or group to which the rule is applied, and then click Save I on the toolbar.
   OR -
- Right-click **Content-Aware Rules**, and then click **Manage**. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, click **Save**.

The Save As dialog box appears.

- 4. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .cwl file.
- 5. In the **File name** box, type the file name you want.
- 6. Click Save.

When you export rules, they are saved in a file with a .cwl extension.

#### To import Content-Aware Rules

1. If you use DeviceLock Management Console, do the following:

- a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Load.
     OR -
  - Select Content-Aware Rules, and then click Load on the toolbar.
     OR -
  - Expand Content-Aware Rules, right-click any user or group to which the rule is applied, and then click Load.
     OR -
  - Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Load**.

- OR -

- Expand Content-Aware Rules select any user or group to which the rule is applied, and then click Load in the toolbar.
   OR -
- Right-click **Content-Aware Rules**, and then click **Manage**. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, click **Load**.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open**.

You can import only one .cwl file at a time.

## **Undefining Content-Aware Rules**

If you deploy DeviceLock policies using DeviceLock Group Policy Manager or DeviceLock Service Settings Editor, in some situations you may want to prevent Content-Aware Rules from being applied to a specific group of client computers. To do so, you need to return the previously defined Content-Aware Rules to the unconfigured state. All undefined DeviceLock settings are ignored by client computers.

#### **To undefine Content-Aware Rules**

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, right-click DeviceLock Settings or DeviceLock Service, and then click Load Service Settings to open the XML file with defined DeviceLock policies.
  - c) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, right-click **Content-Aware Rules**, and then click **Undefine**.

### **Deleting Content-Aware Rules**

You can delete individual Content-Aware Rules when they are no longer required.

#### To delete a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.

- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Expand **Content-Aware Rules**, right-click the user or group to which the rule is applied, and then click **Delete user**.

```
When you delete a user or group, the rule associated with this user or group is automatically deleted.
```

- OR -

- Expand Content-Aware Rules, and then select the user or group to which the rule is applied. In the details pane, right-click the rule associated with this user or group, and then click Delete.
   OR -
- Right-click **Content-Aware Rules**, and then click **Manage**. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group to which the rule is applied. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, select the rule, and then click **Delete** or right-click the rule, and then click **Delete**.

*You can select multiple rules that you want to delete by holding down the SHIFT key or the CTRL key while clicking them.* 

# **Content-Aware Rules for Protocols (Regular Profile)**

Content-Aware Rules extend the protocol access control functionality of DeviceLock by adding comprehensive, content-level protection of corporate data containing confidential company information. Content-Aware Rules enable automatic content inspection of data/files transmitted over the network, detection of sensitive content and enforcement of regulatory policies to ensure protection.

With Content-Aware Rules, you can selectively allow or deny access to specific content transmitted over the network regardless of preset permissions at the protocol – level. You can also use Content-Aware Rules to allow or deny shadow copying of specific content. For flexibility, Content-Aware Rules can be defined on a per-user or per-group basis.

You can configure Content-Aware Rules to apply to access control operations, to shadow copy operations, or both.

The following examples illustrate the use of Content-Aware Rules.

- **Example 1 Using Content-Aware Rules for access control operations**. You can prevent certain users or groups from uploading files containing credit card numbers, telephone numbers and addresses to an FTP server.
- Example 2 Using Content-Aware Rules for shadow copy operations. You
  can specify that IM conversations containing credit card numbers and e-mail
  addresses will be shadow copied for security auditing and incident investigation
  purposes.

**Note:** You can define different online vs. offline Content-Aware Rules for the same user or sets of users. Online Content-Aware Rules (Regular Profile) apply to client computers that are working online. Offline Content-Aware Rules (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define offline Content-Aware Rules for protocols, see "Managing Offline Content-Aware Rules for Protocols."

## **Content-Aware Rules for Access Control Operations**

Content-Aware Rules allow you to do the following:

- Grant access to specified content when access is denied at the protocol-level.
- Deny access to specified content when access is granted at the protocol-level.

Content-Aware Rules also override any rules defined in the Protocols White List.

The following table provides summary information on access rights that can be specified for each protocol in Content-Aware Rules.

#### Content-Aware Rules for Protocols (Regular Profile)

PROTOCOL	ACCESS RIGHTS	DESCRIPTION
FTP	Generic: Outgoing Files	Controls whether the user can upload files with specified content to an FTP server.
	SSL: Outgoing Files	Controls whether the user can upload files with specified content to an FTP server using FTPS.
НТТР	Generic: POST Requests	Controls whether the user can submit Web form data with specified content to a Web server using HTTP.
	Generic: Outgoing Files	Controls whether the user can upload files with specified content to a Web server using HTTP.
	SSL: POST Requests	Controls whether the user can submit Web form data with specified content to a Web server using HTTPS.
	SSL: Outgoing Files	Controls whether the user can upload files with specified content to a Web server using HTTPS.
ICQ/AOL Messenger,	Generic: Outgoing Messages	Controls whether the user can send instant messages with specified content.
IRC, Jabber	SSL: Outgoing Messages	Controls whether the user can send instant messages with specified content using SSL.
Mail.ru Agent, Windows Messenger, Yahoo Messenger	Generic: Outgoing Messages	Controls whether the user can send instant messages with specified content.
SMTP, Web Mail	Generic: Outgoing Messages	Controls whether the user can send e-mail messages with specified content.
	Generic: Outgoing Files	Controls whether the user can send e-mail attachments with specified content.
	SSL: Outgoing Messages	Controls whether the user can send e-mail messages with specified content using SSL.
	SSL: Outgoing Files	Controls whether the user can send e-mail attachments with specified content using SSL.
Social Networks	Generic: Outgoing Messages	Controls whether the user can send messages, comments, and posts with specified content.
	Generic: Outgoing Files	Controls whether the user can send media and other files with specified content to a social networking site.

**Note:** If the No Access permission is set for a protocol and there is a Content-Aware Rule that allows access to specified content for the same protocol, the Send/Receive Data access right is automatically granted to users for this protocol. For more information about this access right, see "<u>Managing</u> <u>Permissions for Protocols.</u>"

When using Content-Aware Rules, consider the following:

- If Content-Aware Rules are defined for both devices and protocols, all access checks are executed in one thread.
- Content-Aware Rules with Deny settings take priority over rules with Allow settings if they apply to the same users or groups.
- Checking the content of files can be a time-consuming operation. You can define a Content verification message to be displayed to users when content inspection is in progress. For detailed information on this message, see "Content verification message" in "Service Options".
- When users try to use protocols to which they are denied access, they receive a Protocols blocked message, if Protocols blocked message is enabled in Service Options. For detailed information on this message, see "Protocols blocked message" in "Service Options".

## **Content-Aware Rules for Shadow Copy Operations**

Before you can use Content-Aware Rules for shadow copy operations, you must turn on shadowing in **Auditing and Shadowing** at the protocol-level. Content-Aware Rules that apply to shadow copy operations filter the shadow copies of data and files transmitted by the user.

PROTOCOL	SHADOWING RIGHTS	DESCRIPTION
FTP	Generic: Incoming Files	Controls whether or not files with specified content downloaded from an FTP server are shadow copied.
	Generic: Outgoing Files	Controls whether or not files with specified content uploaded to an FTP server are shadow copied.
	SSL: Incoming Files	Controls whether or not files with specified content downloaded from an FTP server using FTPS are shadow copied.
	SSL: Outgoing Files	Controls whether or not files with specified content uploaded to an FTP server using FTPS are shadow copied.
НТТР	Generic: Incoming Files	Controls whether or not files with specified content downloaded from a Web server are shadow copied.
	Generic: POST Requests	Controls whether or not Web form data with specified content submitted to a Web server is shadow copied.
	Generic: Outgoing Files	Controls whether or not files with specified content uploaded to a Web server are shadow copied.
	SSL: Incoming Files	Controls whether or not files with specified content downloaded from a Web server using HTTPS are shadow copied.

The following table provides summary information on shadowing rights that can be specified for each protocol in Content-Aware Rules.

## Content-Aware Rules for Protocols (Regular Profile)

PROTOCOL	SHADOWING RIGHTS	DESCRIPTION
	SSL: POST Requests	Controls whether or not Web form data with specified content submitted to a Web server using HTTPS is shadow copied.
	SSL: Outgoing Files	Controls whether or not files with specified content uploaded to a Web server using HTTPS are shadow copied.
ICQ/AOL Messenger, IRC, Jabber	Generic: Incoming Messages	Controls whether or not instant messages with specified content received by the user are shadow copied.
	Generic: Outgoing Messages	Controls whether or not instant messages with specified content sent by the user are shadow copied.
	SSL: Incoming Messages	Controls whether or not instant messages with specified content received by the user using SSL are shadow copied.
	SSL: Outgoing Messages	Controls whether or not instant messages with specified content sent by the user using SSL are shadow copied.
Mail.ru Agent, Windows	Generic: Incoming Messages	Controls whether or not instant messages with specified content received by the user are shadow copied.
Messenger, Yahoo Messenger	Generic: Outgoing Messages	Controls whether or not instant messages with specified content sent by the user are shadow copied.
SMTP, Web Mail	Generic: Outgoing Messages	Controls whether or not e-mail messages with specified content sent by the user are shadow copied.
	Generic: Outgoing Files	Controls whether or not e-mail attachments with specified content sent by the user are shadow copied.
	SSL: Outgoing Messages	Controls whether or not e-mail messages with specified content sent by the user using SSL are shadow copied.
	SSL: Outgoing Files	Controls whether or not e-mail attachments with specified content sent by the user using SSL are shadow copied.
Social Networks	Generic: Outgoing Messages	Controls whether or not messages, comments, and posts with specified content sent by the user are shadow copied.
	Generic: Outgoing Files	Controls whether or not media and other files with specified content uploaded to a social networking site are shadow copied.

## **Configuring Content Detection Settings**

Content-Aware Rules are created based on content groups that enable you to centrally define types of content for which you want to control access. Content groups specify content filtering criteria that will be used to select data to which rules should be applied.

All content groups are stored in the Content Database. The same Content Database is used for both devices and protocols. The Content Database is a part of the DeviceLock Service policy and is also saved in an XML file with service settings that can be created using DeviceLock Management Console, DeviceLock Service Settings Editor, and DeviceLock Group Policy Manager.

There are several types of content groups: File Type Detection groups, Keywords groups, Pattern groups, Document Properties groups, and Complex groups. The sections below describe these groups and how to use them.

## **File Type Detection Content Groups**

File Type Detection groups are used to control access to files based on file types. These groups contain definitions of the file types that make up these groups. A file type definition consists of two properties: a file name extension (for example, DOC) and a description (for example, Microsoft Word document). When you apply a rule based on a File Type Detection group, the rule is applied to all file types included in that group.

DeviceLock includes 34 predefined (built-in) File Type Detection groups that you can use to set up the desired configuration of permissions and/or shadow copy operations. You can use the built-in content groups as they are, create their editable copies (duplicates) or create your own content groups to suit your particular organization's needs.

BUILT-IN FILE TYPE DETECTION GROUPS	
Archives Audio, Video & Flash BlackBerry Common Object File Format (COFF) Database Executable Fax Documents FileMaker Pro Fonts Help Files Images, CAD & Drawing Lotus SmartSuite MS Access MS Excel MS InfoPath MS Money MS OneNote	MS Outlook & Outlook Express MS PowerPoint MS Project MS Publisher MS Visio MS Windows Installer MS Windows Memory Dump MS Word MS Words OpenOffice, StarOffice, OpenDocument, etc. PDF, PostScript, & XPS Documents QuickBooks, Quicken, TurboTax & etc. Rich Text Format Security Certificates Text, HTML & XML Virtual Machines WordPerfect Office

The following table lists these predefined content groups:

**Note:** Content-Aware Rules support Word To Go, Sheet To Go, and Slideshow To Go formats for Palm devices. Word To Go format is included in the MS Word and Rich Text Format built-in content groups, Sheet To Go format is included in the MS Excel built-in content group, while Slideshow To Go format is included in the MS PowerPoint built-in content group.

Microsoft Word or Rich Text Format (RTF) files, Excel files and PowerPoint files can be transferred to a Palm device using the Documents To Go application. The Documents To Go application converts these files to special formats: Word and RTF files are converted to Word To Go format, Excel files are converted to Sheet To Go format, while PowerPoint files are converted to Slideshow To Go format. The converted files are automatically downloaded to the Palm when users synchronize.

With built-in content groups, you can quickly create and apply rules without having to define your own content groups.

**Note:** You can view file type definitions that are included in the built-in File Type Detection groups but you cannot edit or delete them. For information on how to view the built-in content groups, see "<u>Viewing Built-in Content Groups</u>."

#### **Creating Custom File Type Detection Groups**

You can define Content-Aware Rules based on your own (custom) content groups if the predefined content groups included with DeviceLock do not meet your requirements. Custom File Type Detection content groups enable you to specify any file types that you want in the same group to better meet your individual business needs.

For example, suppose you need to grant certain users access to Word, Excel, PDF documents and graphic files. To do this, first you create a new File Type Detection content group that represents these document content types. Then you define a rule based on this custom content group.

#### To create a custom File Type Detection group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -

• Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

Content-Aware Rules						2
Content Database						
Description					Туре	^
ABA Routing Number					Pattern (	b.
Acquisition					Keyword	s (
Admission Discharge					Keyword	\$(
American Address					Keyword	51
American Name					Keyword	5(
R Archives					File Type	D
R Audio, Video & Flash					File Type	DV
<						>
Contract Contract of Contract						
Content-Aware Rules	Duplicate	Add Group 💌 🛛 Ed	It Group Delete Gro	up Show: All Typ	pes	~
Add Test Group	Duplicate Rules	Add Group	It Group	up Show: All Typ	pes	~
Content-Aware Rules	Rules Descript	Add Group	Action(s)	Applies To	Protocol(s)	•
Add Test Group	Rules Descript	Add Group 💌 Ed	Action(s)	Applies To	Protocol(s)	

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **File Type Detection**.

Add File Type Detection Group				?
Content Group Name: 1		Available Content		
Extension Description		Find Find F	Previous Filter	
	< <	Extension	Description a Colic data yEnc Encoded XNA Game Studio resource HP Xine compressed X oursor Xbox 360 DIRS container data file Xbox 360 DIRS container data file Xbox 360 CON container data file Works 4.0 for Macintosh WIDEV data (generic) WDDX packet OptionSoft WinCode encoded FrontPage_VTI_bogImfo YmGrypt encrypted data VERICUT Model file Unreal Package UHBC compressed Trend Micro Virus Pattern Texas Instruments Calculators Pri The Witcher save game	
		<	121	>

The Add File Type Detection Group dialog box appears.

- 5. In the left pane of the **Add File Type Detection Group** dialog box, under **Content group**, type the name of the new content group in the **Name** box.
- 6. In the right pane of the **Add File Type Detection Group** dialog box, under **Available Content**, select any file type you want to add to the new content group, and then click the left single-arrow button

You can select multiple file types by holding down the SHIFT key or the CTRL key while clicking them.

To remove single file types from the content group, use the right single-arrow button To add or remove all available file types to or from the content group at the same time, use the left double-arrow button is or right double-arrow button is.

**Note:** You can search the available content database for specific file types by extension or description. You can use wildcards such as asterisks (\*) and question marks (?) to search for a specific group of file types. To find a specific file type or specific group of file types, under **Available Content**, type an extension or description with or without wildcards in the search string, and then click **Find**. To filter file types, click **Filter**. To remove the filter, apply it to an empty string.

An asterisk (\*) replaces an unlimited number of characters. The question mark (?) replaces a single character. You can use these wildcards in any position and in any quantity.

7. Click **OK** to close the **Add File Type Detection Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

## **Keywords Content Groups**

Keywords groups are used to control access to data/files based on specified keywords or phrases.

DeviceLock includes 157 predefined (built-in) Keywords groups that you can use to set up the desired configuration of permissions and/or shadow copy operations. You can use the built-in content groups as they are, create their editable copies (duplicates) or create your own content groups to suit your particular organization's needs.

The following table lists these predefined content groups:

Accounting Documentation Terms Accounting Documentation Types Acquisition Active substance Admission Discharge Adult Keywords American Address American Name Bank ABA	Production Charges Profanity Profiles Profit Loss Project Names Project Release Dates Property Racism Keywords Resume
Bank ACN I	Russian: Account Statement
Bank STMT	Russian: Accounting Documentation
Board Meeting	Russian: Accounting Documentation Terms

#### **BUILT-IN KEYWORDS GROUPS**

#### **BUILT-IN KEYWORDS GROUPS**

Breach of Obligation	Russian: Accounting Documentation Types
Breach of Standards	Russian: Bank Account
Breach of the Law	Russian: Bank Operations
Business Documentation	Russian: Banking Operations Participants
Business Documentation Terms	Russian: Breach of Commitment
Business Documentation Types	Russian: Breach of Law
Business Rivals	Russian: Business Documentation
Business Trips & Meetings	Russian: Business Documentation Terms
C# Source Code	Russian: Business Documentation Types
C/C++ Source Code	Russian: Business Partners
Cellular Operator Call Log	Russian: Business Trips & Meetings
COBOL Source Code	Russian: Company Development Plan
Common Disease	Russian: Compensation and Benefits
Common Medical Terms	Russian: Confidential Information
Company Development	Russian' Corporate Canital
Compensation and Benefits	Russian' Corporate Property
Compliance Report	Russian' Evipences
Confidential	Russian, Expenses
Confidential Partners Information	Russian, Financial Information
Credit Papart	Russian, Financial Inivitiduuli Russian, Financial Report
Credite	Russiani, Financial Terme
Discontent	Russiani: Findricial Terms
Disconditing Information	Russiani: Filing
Driver S License	Russian: Insurance
Employer Identification Number	Russian: Internal Payments
Ethnicity	Russian: Investors and Investments
Executive Job Searches	Russian: Labor Law
Failures	Russian: Loans and Credits
Financial Report	Russian: Manufacturing
Financial Statements	Russian: Market Development Plan
Firing	Russian: Medicinal Active Substances
FITS Date & Time	Russian: Medicinal Drugs
FITS File Checksum	Russian: Noncompliant
FITS File Descriptors	Russian: Passwords and Access Codes
FITS Hierarchical file grouping	Russian: Physical Security
FITS Instrumentorum	Russian: Prices
FITS Non-standard	Russian: Project Documentation
FITS Observations	Russian: Project Names
FITS Standard	Russian: Project Versions
Gambling	Russian: Projects Release Date
Grades	Russian: Technology
HCFA (CMS) 1500 Form	Russian: User Names
HIPAA - Diseases	Russian: Working Conditions
HIPAA HCPCS	Sales Forecast
HIPAA ICD9	Sarbanes-Oxley Sensitive
HIPAA NDC Classes	Security
HIPAA NDC Dosages	Security Agencies
HIPAA NDC Listing	Sensitive Disease
HIPAA NDC Routes	Sexual Language
Illegal Drugs	Social Security
Innovations	SPAM
Internet Slang Abbreviations	Sports
Investments	Staff Training
lava Source Code	Substance Abuse
Market Development	Suspicious Activity Report
Medical Diagnosis	Technology

#### **BUILT-IN KEYWORDS GROUPS**

Medical Record Numbers	UBO4 Form
MEMO	US Birth Date
Network Security	US Birth Place
Partner Names	US Expiry Date
Password	User Name
Payments	VB Source Code
PCI GLBA	Violence
Perl Source Code	Weapon Keywords
Price List	Wire Transfer
Prices	Working Conditions
Pro Earnings	

With built-in content groups, you can quickly create and apply rules without having to define your own content groups.

**Note:** You can view keywords that are included in the built-in Keywords groups but you cannot edit or delete them. For information on how to view the built-in content groups, see "<u>Viewing Built-in Content</u> <u>Groups</u>."

#### **Creating Custom Keywords Groups**

You can define Content-Aware Rules based on your own (custom) content groups if the predefined content groups included with DeviceLock do not meet your requirements. Custom Keywords content groups enable you to specify any keywords that you want in the same group to better meet your individual business needs.

#### To create a custom Keywords group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

about Databases					
Description					une
ABA Routing Number				P	attern (b.
Acquisition				к	eywords (
Admission Discharge				К	eywords (
Adult Keywords				ĸ	eywords (
American Address				ĸ	eywords (
Anterican Name				F	le Type D
Audio, Video & Flash				F	le Type D
					>
Add Test Comm	Dunkrate Add Group In	Edit Genue	Contra Chaur	All Turner	
ntent-Aware Rules Jsers	Rules				
ntent-Aware Rules Jsers	Rules				
istent-Aware Rules Isers Users A	Rules Description Type	Action(s	) Applies T	o Protocol(s)	
ntent-Aware Rules Isers Users +	Rules Description Type	Action(s	i) Applies T	e Protocol(s)	
ntent-Aware Rules Joers Users A	Rules Description Type	Action(s	) Applies T	o Protocol(s)	
ntent-Aware Rules Isers Users +	Rules Description Type	Action(s	i) Applies T	o Protocol(s)	
ntent-Aware Rules Jsers Users A	Rules Description Type	Action(s	i) Applies T	e Protocol(s)	
ntent-Aware Rules Jsers Users A	Rules Description Type	Action(s	i) Applies T	e Protocol(s)	
Isers Add Delete	Rules Description Type Delete Edt	Action(s	i) Applies T	e Protocol(s)	Save
Isers Add Delete	Rules Description Type Delote Edk	Action(s	i) Applies T	e Protocol(s)	Save
Isers Add Delete	Rules Description Type Delete Edit	e Action(s	i) Applies T	e Protocol(s)	Save

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Keywords**.

🔍 Add Key	words Group	? 🛚
Name: Description:		
Condition:	Match any keyword(s)	Threshold: 1
Keyword	s	Case Sensitive Whole Word
Add	Delete	Load
		OK Cancel

The Add Keywords Group dialog box appears.

5. In the **Add Keywords Group** dialog box, do the following:

USE THIS	TO DO THIS
Name	Specify the name of the group.
Description:	Specify a description for the group.

USE THIS	TO DO THIS
Condition:	<ul> <li>Specify conditions for firing rules associated with this content group. To do so, in the <b>Condition</b> list, click any of the following options:</li> <li><b>Match any keyword(s)</b> indicates that a rule associated with this content group is activated every time any of the specified keywords is found within text data.</li> <li><b>Match all keyword(s)</b> indicates that a rule associated with this content group is activated every time all of the specified keywords are found within text data.</li> <li><b>Only when combined score exceeds (or equal to) threshold</b> indicates that a rule associated with this content group is activated every time the total number (sum) of occurrences of all found keywords within text data equals or exceeds the threshold number of occurrences of the keywords.</li> </ul>
Threshold	Specify the threshold number of occurrences of the keywords. This number can range from 0 to 65535. This property requires a value if you selected the <b>Only when combined score exceeds (or equal to) threshold</b> option.
Keywords	Specify words and phrases that must occur within text data. Double- click under <b>Keywords</b> to enter a keyword or phrase.
Case Sensitive	Determine the case sensitivity of the keywords. Select the <b>Case</b> <b>Sensitive</b> check box to specify a case-sensitive comparison of the keywords (for example, the words "test" and "Test" will be treated as different keywords.). Clear the <b>Case Sensitive</b> check box to specify a case-insensitive comparison of the keywords (for example, the words "test" and "Test" will be treated as the same keyword).
Whole Word	Specify keyword matching options. Select the <b>Whole Word</b> check box to specify the exact match option (allows you to find an exact match of your keyword). Clear the <b>Whole Word</b> check box to specify the broad match option (allows you to find all grammatical variations of your keyword).
Weight	Specify the degree of importance for each keyword or phrase. Weight is used to count the number of occurrences of the specified keywords within text data. This property requires a value if you selected the <b>Only when combined score exceeds (or equal to) threshold</b> option.
	Possible values: Heavy, Above Normal, Normal (default value), Below Normal, Light.
	These weight values are interpreted as follows:
	<b>Heavy</b> weight indicates that each keyword occurrence is counted as three occurrences. This value is the highest.
	<b>Above Normal</b> weight indicates that each keyword occurrence is counted as two occurrences.
	<b>Normal</b> weight indicates that each keyword occurrence is counted as one occurrence.
	<b>Below Normal</b> weight indicates that two keyword occurrences are counted as one occurrence.

USE THIS	TO DO THIS
	<b>Light</b> weight indicates that three keyword occurrences are counted as one occurrence. This value is the lowest.
Add	Specify keywords and phrases. Click <b>Add</b> to enter a keyword or phrase.
Delete	Delete a keyword. To do so, select the keyword you want to delete, and then click <b>Delete</b> . You can select multiple keywords by holding down the SHIFT key or the CTRL key while clicking them.
Load	Import a list of keywords from a tab-delimited text file.

6. Click **OK** to close the **Add Keywords Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

## **Pattern Content Groups**

Pattern groups let you control access to text data using patterns of text described by Perl regular expressions. Patterns provide a flexible and powerful way to automatically detect potentially sensitive content (for example, credit card numbers, Social Security numbers, e-mail addresses, and phone numbers) within text data.

For more information on creating and using Perl regular expressions, refer to the <u>Perl</u> regular expressions quick start tutorial and <u>Perl regular expressions tutorial</u>.

DeviceLock includes 45 predefined (built-in) Pattern groups that you can use to set up the desired configuration of permissions and/or shadow copy operations. You can use the built-in content groups as they are, create their editable copies (duplicates) or create your own content groups to suit your particular organization's needs.

The following table lists these predefined content groups:

#### **BUILT-IN PATTERN GROUPS**

ABA Routing Number	Russian: Main State Registration Number
BIC (ISO 9362)	Russian: Motorcycle Numbers
Canadian Social Insurance Number	Russian: Passport
Credit Card Number	Russian: Pension Insurance Number
Email Address	Russian: Post Code
European VAT Number	Russian: Taxpayer Identification Number
GPS Data (RMC String)	Russian: Telephone Number
IBAN	Russian: Trailer Numbers
International Telephone Number	Russian: Vehicle Registration Document
IP Address	SQL Queries
ISO Date	TCP/UDP Port Number
MAC Address	Time (12/24h)
Microsoft Windows Product Key	UK National Insurance Number
Russian: Address	UK Phone Number

#### **BUILT-IN PATTERN GROUPS**

Russian: Auto Insurance Number	UK Post Code
Russian: Bank Account Number	UK Tax Code
Russian: BIC	Uniform Resource Locator (URL)
Russian: Car Numbers	US Date
Russian: Classification of Economic	US Phone Number
Activities	US Social Security Number
Russian: Classification of Enterprises and	US Zip Code
Organizations	VIN
Russian: Driver's License Number	
Russian: Health Insurance Number	
Russian: International Passport	

With built-in content groups, you can quickly create and apply rules without having to define your own content groups.

**Note:** You can view regular expression patterns that are included in the built-in Pattern content groups but you cannot edit or delete them. For information on how to view the built-in content groups, see "<u>Viewing Built-in Content Groups</u>."

#### **Creating Custom Pattern Groups**

You can define Content-Aware Rules based on your own (custom) content groups if the predefined content groups included with DeviceLock do not meet your requirements. Custom Pattern content groups enable you to specify any pattern that you want to use to identify sensitive information within text data.

#### To create a custom Pattern group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

M Content-Aware Rules			2 🛛
Content Database			
Description 국, ABA Routing Number 국, Acquisition 국, Aduit Keywords 국, Aduit Keywords 국, Anerican Address 국, American Name 국, Archives 국, Audio, Yideo & Flash			Type Pattern (b. Keywords ( Keywords ( Keywords ( Keywords ( File Type D File Type D
Add Test Grap Durk	Add Grann La Colle G	count Delete Group Show All Ty	
Content-Aware Rules	Rules Description Type	Action(s) Applies To	Protocol(s)
Add Delete	Delete Edit	OK	Load Save Cancel Apply

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Pattern**.

🔍 Add Pat	tern Group		2 🛛
Name:			
Description:			
Expression:			Validate
Validation:	No Validation		~
Condition:	Greater than 💌	1	Advanced >>
Test sample:			
			OK Cancel

The Add Pattern Group dialog box appears.

5. In the Add Pattern Group dialog box, do the following:

USE THIS	TO DO THIS	
Name	Specify the name of the group.	
Description:	Specify a description for the group.	

USE THIS	TO DO THIS
Expression	Specify a pattern by creating a regular expression. For information on how to create Perl regular expressions, refer to the <u>Perl regular</u> expressions quick start tutorial and <u>Perl regular expressions tutorial</u> .
Validate	Check regular expression syntax.
Validation	Perform the actual validation on the potential matches returned by the regular expression. The following options are available: <b>No validation</b> (this option is selected by default), <b>ABA Routing Number</b> , <b>Canadian</b> <b>Social Insurance Number</b> , <b>Credit Card Number (All)</b> , <b>Credit Card</b> <b>Number (American Express)</b> , <b>Credit Card Number (Diners</b> <b>Club)</b> , <b>Credit Card Number (Diners Club En Route)</b> , <b>Credit Card</b> <b>Number (Discover)</b> , <b>Credit Card Number (JCB)</b> , <b>Credit Card</b> <b>Number (Laser)</b> , <b>Credit Card Number (Maestro)</b> , <b>Credit Card</b> <b>Number (Master Card)</b> , <b>Credit Card Number (Solo)</b> , <b>Credit Card</b> <b>Number (Switch)</b> , <b>Credit Card Number (Visa)</b> , <b>Credit Card</b> <b>Number (Visa Electron)</b> , <b>Date</b> , <b>Date (ISO)</b> , <b>Email Address</b> , <b>European VAT Number</b> , <b>IBAN</b> , <b>IP Address</b> , <b>LUHN Checksum</b> , <b>Russian Bank Account Number</b> , <b>Russian Health Insurance</b> <b>Number</b> , <b>Russian Taxpayer Identification Number</b> , <b>Russian</b> <b>Main State Registration Number</b> , <b>Russian Classification Of</b> <b>Enterprises And Organizations</b> , <b>UK National Insurance Number</b> , <b>UK Phone Number</b> , <b>UK Post Code</b> , <b>UK Tax Code</b> , <b>URL</b> , <b>US Social</b> <b>Security Number</b> .
Condition:	Specify conditions for firing rules associated with this content group. To do so, in the <b>Condition</b> list, click any of the following options:
	• Less than or = indicates that a rule associated with this content group is activated every time the number of matches returned by the regular expression is less than or equal to the specified number.
	<ul> <li>Equal to indicates that a rule associated with this content group is activated every time the number of matches returned by the regular expression is equal to the specified number.</li> </ul>
	<ul> <li>Greater than or = indicates that a rule associated with this content group is activated every time the number of matches returned by the regular expression is greater than or equal to the specified number.</li> </ul>
	• <b>Between</b> indicates that a rule associated with this content group is activated every time the number of matches returned by the regular expression is within the specified range.
Advanced	Quickly test your regular expression pattern on sample data. Click <b>Advanced</b> to display or hide the <b>Test sample</b> box.
Test sample	Enter a test string and view the result. DeviceLock supports real-time color highlighting of test results. All matches are highlighted in green, while strings that do not match the pattern are highlighted in red.

## 6. Click **OK** to close the **Add Pattern Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

## **Document Properties Content Groups**

Document Properties groups are used to control access to files based on file properties such as file name, size, etc. You can also use a Document Properties content group to control access to password-protected documents and archives as well as text images.

**Note:** The AND logic is applied to all file properties specified within a Document Properties group. For example, if you want to control access to files larger than 5 megabyte (MB) in size and password-protected documents and archives, you should create two separate Document Properties groups: one group for files larger than 5 MB in size and another group for password-protected documents and archives. If you specify these file properties within the same Document Properties group and then create a Content-Aware Rule based on this content group, this rule will control password-protected documents and archives that are larger than 5 MB.

There are no predefined (built-in) Document Properties content groups to use. The following procedure describes how to create your own Document Properties group.

#### To create a Document Properties group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

tent Database Description Type ABA Routing Number Acquisition Pattern (h Acquisition Admission Discharge							?
ABA Routing Number ABA Routing Number ABA Routing Number Acquisition Admission Discharge Aduk Keywords American Address American Name Archives Archives Archives Archives Archives Archives Archives Archives Archives Archives Archives Archives Archives Archives Audio, Video & Flash Test Group Duplicate Add Group ▼ Edit Group Delete Group Show: All Types Show: All Types	intent Database						
ABA Routing Number     Pattern (b       Acquisition     Keywords       Admission Discharge     Keywords       Adult Keywords     Keywords       Adult Keywords     Keywords       American Adress     Keywords       Arthives     File Type       Audio, Video & Flash     File Type       Add     Test Group     Duplicate       Add     Test Group     Duplicate       Add     Test Group     Duplicate	Description					T	ype 🧭
Acquisition     Keywords       Admission Discharge     Keywords       Adult Keywords     Keywords       Anerican Address     Keywords       Anerican Name     Keywords       Anchives     File Type       Audio, Video & Flash     File Type       Add     Test Group     Duplicate       Add     Test Group     Duplicate       Add     Rules     File Type	ABA Routing Number					Pa	ttern (bi
Admission Discharge Keywords Adult Keywords Keywords American Address Keywords Ancerican Name Keywords Anchives File Type Audio, Video & Flash File Type Audio, Video & Flash File Type Add Test Group Duplicate Add Group ▼ Edit Group Delete Group Show: All Types Rent-Aware Rules	Acquisition					Ke	ywords (
Anderican Address Keywords Keywords Keywords Anerican Name Keywords Keywords Anerican Name Keywords Keywords Anerican Name File Type I Audio, Wdeo & Flash File Type I Audio, Wdeo & Flash File Type I Add Group I♥ Edit Group Delete Group Show: All Types Itent-Aware Rules Rules Rules I Audio I Add Group I♥ Edit Group Delete Group Show: All Types Itent-Aware Rules I Audio I Add Group I♥ Edit Group Delete Group Show: All Types Itent-Aware Rules I Add Group I♥ Edit Group Delete Group Show: All Types Itent-Aware Rules I Add Group I♥ Edit Group Delete Group Show: All Types I Add Group I♥ Edit Group Delete Group Show: All Types I Add Group I♥ Edit Group I♥ Edit Group Delete Group Show: All Types I Add Group I♥ Edit Group Delete Group Show: All Types I Add Group I♥ Edit Group Delete Group Show: All Types I Add Group I♥ Edit Group Delete Group Show: All Types I Add Group I♥ Edit Group Delete Group Show: All Types I Add Group I♥ Edit Group I♥	Admission Discharge					Ke	sywords (
Anerican Nares  Anerican Nare  Anerican Nare  Archives  Archives  File Type  Audio, Video & Flash  File Type  Add Test Group Duplicate  Add Group I  Edit Group Delete Group Show: All Types  tent-Aware Rules  File Type  Audio  File Type  File Type File Type File Type  File Type File Type File Type File Type File Type File Type File Type File Type File Type File Type File T	Adult Keywords					Ke	rywords (
Archives File Type I Audio, Video & Flash File Type I Add Test Group Duplicate Add Group I Edit Group Delete Group Show: All Types Itent-Aware Rules Sers Rules	American Name					Ke	symonds (
Audio, Video & Flash File Type Add Test Group Duplicate Add Group I Edit Group Delete Group Show: All Types tent-Aware Rules sers Rules	Archives					Fi	e Type D
Add Test Group Duplicate Add Group I Edit Group Delete Group Show: All Types tent-Aware Rules sers Rules	Audio, Video & Flash					Fé	e Type D
Add Test Group Duplicate Add Group I Edit Group Delete Group Show: All Types tent-Aware Rules sers Rules	1						>
tent-Aware Rules sers Rules Rules	Add Test Group D	uplicate Add G	roup I	Group Delete Gro	Show: All Ty	pes	
	ntent-Aware Rules	- Dudes					
Users  Uescription Type Action(s) Applies To Protocol(s)	intent-Aware Rules Users	Rules					
	tent-Aware Rules Ivers	Rules Description	Туре	Action(s)	Applies To	Protocol(s)	
	ntent-Aware Rules Jsers Users +	Rules Description	Туре	Action(s)	Applies To	Protocol(s)	
	ntent-Aware Rules Jsers Users +	Rules Description	Туре	Action(s)	Applies To	Protocol(s)	
Add Delete Edit Load Save	Add Delete	Rules Description Delete	Type	Action(s)	Applies To	Protocol(s)	Save

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Document Properties**.

lame:	1				
eccription:	[				
Droportion					
File name:	-				~
Modified:	Not energiad	07 /26/	2010 03 57 AM	07 /26/2010 03/57	ALL V
Modeled.	Noc specified	017207	2010 03:57 Mm	07 72672010 03:57	AIM Y
File size:	Not specified	• 0	÷ 0	bytes	Y
Passwor	d protected				
Text ext	raction not supp	orted			
Contains	text	\$			
Accessed by	process:				~
Accessed by	process:				~

The Add Document Properties Group dialog box appears.

5. In the Add Document Properties Group dialog box, do the following:

USE THIS	TO DO THIS
Name	Specify the name of the group.

USE THIS	TO DO THIS
Description:	Specify a description for the group.
File name	Specify the file names. You can use wildcards, such as asterisks (*) and question marks (?). For example, type <b>*.txt</b> to specify all files that have the .txt extension. Multiple file names must be separated by a semicolon (;), for example, <b>*.doc; *.docx</b> .
	An asterisk (*) replaces an unlimited number of characters. The question mark (?) replaces a single character.
Modified	<ul> <li>Specify the last modification date/time of the file. To do so, in the Modified list, click any of the following options:</li> <li>Not specified (this option is selected by default)</li> <li>Before than indicates that the file's modified date/time must be earlier than the specified date/time.</li> <li>After than indicates that the file's modified date/time must be later than the specified date/time.</li> <li>Between indicates that the file's modified date/time must fall within the specified date/time range.</li> <li>Not older than indicates that the file's modified date/time must fall within the specified date/time range.</li> <li>Older than indicates that the file's modified date/time must be older than the specified number of seconds, minutes, days, weeks, months, and years.</li> <li>Older than indicates that the file's modified date/time must be older than the specified number of seconds, minutes, days, weeks, months, and years.</li> </ul>
File size	<ul> <li>Specify the file size in bytes, kilobytes, megabytes, gigabytes or terabytes. To do so, in the File size list, click any of the following options:</li> <li>Not specified (this option is selected by default)</li> <li>Equal to indicates that the file(s) must have a size that is equal to the size you specify.</li> <li>Less than indicates that the file(s) must have a size that is less than the size you specify.</li> <li>More than indicates that the file(s) must have a size that is more than the size you specify.</li> <li>Between indicates that the file size must fall within the specified range.</li> </ul>
Password protected	Detect and control access to password-protected archives, PDF files, and Microsoft Office documents (.doc, .xls, .ppt, .docx, .xlsx, .pptx). If you select the <b>Password protected</b> check box for a Document Properties group and then create a Content-Aware Rule based on this content group, this rule will control access to password-protected archives, PDF files, and Microsoft Office documents. Clear the <b>Password protected</b> check box if you do not want to detect and control access to password-protected archives, PDF files, and Microsoft Office documents. For information on supported archive formats, see

USE THIS	TO DO THIS		
	the description of the "Inspection of files within archives" feature.		
Text extraction not supported	Control access to unsupported file formats. If you select the <b>Text</b> <b>extraction not supported</b> check box for a Document Properties group and then create a Content-Aware Rule based on this content group, this rule will control access to all files in an unsupported format. All supported file formats are listed in the " <u>Extending DeviceLock</u> <u>Functionality with ContentLock and NetworkLock</u> " section.		
Contains text	Detect and control access to images based on whether or not they contain text. If you select the <b>Contains text</b> check box for a Document Properties group and then create a complex Content-Aware Rule based on this content group and the built-in Images, CAD & Drawing content group (File Type Detection) combined by the AND operator, this rule will check whether supported image files contain text and control access to text images. Clear the <b>Contains text</b> check box if you do not want to detect and control access to text images. For information on the supported image files, see the description of the " <u>Text in picture detection</u> " feature.		
	If you select the <b>Contains text</b> check box, specify the amount of text that images must contain. The amount of text is expressed as a percentage of the total image area. For example, if text occupies ½ of the image, the amount of text makes 50%. If an image contains only text, the amount of text is 100%.		
	<b>Note:</b> The <b>Contains text %</b> option also applies to other <u>supported file</u> <u>formats</u> . In this case, the percentage means the ratio of the text size in characters to file size in bytes.		
Accessed by process	Specify the name of the process accessing the document's file. You can use wildcards, such as asterisks (*) and question marks (?). Multiple process names must be separated by a semicolon (;), for example, <b>explorer.exe; notepad.exe</b> .		

6. Click **OK** to close the **Add Document Properties Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

## **Complex Content Groups**

Complex groups use Boolean expressions to select data for which you want to control access. These groups can include any combination of built-in or custom content groups (File Type Detection, Keywords, Pattern, and Document Properties groups) linked with any number of the standard logical operators. Each content group is treated as a single filter criterion that can be included in your Boolean expression. By using multiple content groups, you can create complex filters to identify sensitive content of data transmitted over the network.

The following table lists the logical operators in order of precedence from highest to lowest.

OPERATOR	MEANING	
NOT	Logical negation of a filter criterion	
AND	Both filter criteria must apply	
OR	Either filter criterion can apply	

You can use parentheses to modify the precedence of operators and force some parts of an expression to be evaluated before others. Nested criteria enclosed in parentheses are evaluated in inner-to-outer order. Multiple levels of nesting are supported. A complex group can contain a maximum of 30 content groups.

There are no predefined (built-in) Complex content groups to use. The following procedure describes how to create your own Complex group.

#### To create a Complex group

1. If you use DeviceLock Management Console, do the following:

- a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand Protocols.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

(a) Content-Aware Rules				2 🛛
Content Database				
Description  ABA Routing Number  Acquisition				Type Pattern (b. Keywords (
Admission Discharge     Adult Keywords     American Address				Keywords ( Keywords ( Keywords (
American Name     Archives     Audio, Video & Flach				Keywords ( File Type D
<				
Add Test Group Duplic	ate Add Group 💌	Edit Group Delete Group	Show: All Type	s 💌
Content-Aware Rules Users	Rules			
Users A	Description Type	Action(s)	Applies To	Protocol(s)
Add Delete	Delete Edit		(	Load Save
			ок	Cancel Apply

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Complex**.

The Add Complex Group dialog box appears.

R Add Complex Group		2 🔀
Name:		
Description:		
Add Insert View Delete		A V
NOT (	Criteria	) AND/OR
Result		
		2
		0
Cicor Valdate		OK Cancel

5. In the **Add Complex Group** dialog box, do the following:

#### **Content-Aware Rules for Protocols (Regular Profile)**

USE THIS	TO DO THIS		
Name	Specify the name of the group.		
Description:	Specify a description for the group.		
Add	Add the desired content groups from the Content Database. To do so, click <b>Add</b> to open the <b>Content Groups</b> dialog box. In the <b>Content Groups</b> dialog box, under <b>Content Database</b> , select the desired content group, and then click <b>OK</b> .		
	You can select multiple content groups by holding down the SHIFT key or the CTRL key while clicking them.		
	<i>To view information about a content group, select the desired group, and then click View Group.</i>		
	The content groups you added appear in the Criteria column in the Add Complex group dialog box. Each content group you add is treated as a single filter criterion that can be included in your Boolean expression.		
Insert	Insert a content group from the Content Database before the currently selected group in the <b>Criteria</b> column. To do so, click <b>Insert</b> to open the <b>Content Groups</b> dialog box. In the <b>Content Groups</b> dialog box, under <b>Content Database</b> , select the desired content group, and then click <b>OK</b> .		
View	View information about the currently selected group in the <b>Criteria</b> column.		
Delete	Delete the selected group from the <b>Criteria</b> column.		
ΝΟΤ	Join each content group you select with the logical NOT operator. To do so, select the desired group in the <b>Criteria</b> column, and then select the appropriate check box in the <b>Not</b> column.		
AND/OR	Join each content group you select with the logical AND or OR operator. To do so, select the desired group in the <b>Criteria</b> column, and then click either <b>AND</b> or <b>OR</b> in the appropriate list in the <b>AND/OR</b> column.		
Clear	Clear the current list of content groups in the <b>Criteria</b> column.		
Validate	Validate your expression. If the expression was defined incorrectly (for example, an opening parenthesis was not matched with a closing parenthesis), you receive an error message.		

#### 6. Click **OK** to close the **Add Complex Group** dialog box.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

## **Viewing Built-in Content groups**

You can view any built-in content groups but you cannot edit or delete them.

#### To view a built-in content group

1. If you use DeviceLock Management Console, do the following:

- a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any built-in group you want to view, and then click **View Group**.

## **Duplicating Built-in Content groups**

You cannot edit the built-in content groups but you can create and use their editable copies (duplicates) to suit your particular organization's needs.

#### To duplicate a built-in content group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

- 4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any built-in group you want to duplicate, and then click **Duplicate**.
- 5. In the dialog box that opens, edit the content group as required, and then click **OK**.

The new content group you created is added to the existing list of content groups under Content Database in the upper pane of the Content-Aware Rules dialog box.

## **Editing and Deleting Custom Content Groups**

You can modify or delete custom content groups at any time.

#### To edit or delete a custom content group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

- 4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any custom group you want to edit or delete.
- 5. Click **Edit Group** to modify the selected content group. In the dialog box that opens, make the required changes, and then click **OK**.

- OR -

Click **Delete Group** or press the DELETE key to delete the selected content group.

6. In the **Content-Aware Rules** dialog box, click **OK** or **Apply** to apply the changes.

## **Testing Content Groups**

You can test any built-in or custom content group to see whether specified files match with it. By using these tests, you can verify that the rules that are created based on the content groups meet your specific business requirements.

#### To test a content group

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

4. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select any content group you want to test, and then click **Test Group**.

You can test only one group at a time.

The Open dialog box appears.

- 5. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to use for testing the specified content group.
- 6. In the folder list, locate and open the folder that contains the file.
- 7. Click the file, and then click **Open**.

The Result message box is displayed. If the file matches with the specified content group, the Result message box contains the following text: "Selected file matches with the group." If the file does not match with the specified content group, the Result message box contains the following text: "Selected file does not match with the group."

When testing is in progress, the console stops responding (hangs)

## **Managing Content-Aware Rules**

Managing Content-Aware Rules involves the following tasks:

- Defining Content-Aware Rules
- Editing Content-Aware Rules
- Copying Content-Aware Rules
- Exporting and importing Content-Aware Rules
- Undefining Content-Aware Rules
- Deleting Content-Aware Rules

You can manage Content-Aware Rules using DeviceLock Management Console, DeviceLock Group Policy Manager, or DeviceLock Service Settings Editor.

## **Defining Content-Aware Rules**

Content-Aware Rules are created based on either the built-in or custom content groups. For detailed information on these groups, see "<u>Configuring Content Detection Settings</u>."

#### To define a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

						?
intent Database						
Description					Туре	^
ABA Routing Number					Pattern (t	x
C Acquisition					Keywords	:(
Admission Discharge					Keywords	-
Adult Keywords					Keywords	
American Name					Keywords	
Archives					File Type	D
💐 Audio, Video & Flash					File Type	Dv
(					2	8
Add Test Group	Duplicate A	Add Group	Edit Group Delete Group	Show: All Typ	pes	~
2700 BD						

4. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

5. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups for which you want to define the rule, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules dialog box.

To delete a user or group, in the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group, and then click **Delete** or press the DELETE key.

6. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the users or groups for which you want to define the rule.

*You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.* 

7. In the upper pane of the **Content-Aware Rules** dialog box, under **Content Database**, select the desired content group, and then click **Add**.

**Note:** You can specify only one content group for a Content-Aware Rule.

The Add Rule dialog box appears.

a) Add Rule	25
Description: Confidential Applies to Permissions Shadowing Protocol(s):	
Actions	
User's Rights	Allow Deny

8. In the **Add Rule** dialog box, in the **Description** box, type the name of the Content-Aware Rule.

By default, the Content-Aware Rule has the same name as the specified content group but you can enter a different name.

- 9. Under **Applies to**, specify the type of operation associated with the rule. The available options are:
  - **Permissions**: Specifies that the rule will apply to access control operations.
  - **Shadowing**: Specifies that the rule will apply to shadow copy operations.
  - **Permissions**, **Shadowing**: Specifies that the rule will apply to both access control and shadow copy operations.
- 10. Under **Protocol(s)**, select the appropriate protocol(s) you would like this rule to be applied to.

Content-Aware Rules can be applied to the following protocols: FTP, HTTP, ICQ/AOL Messenger, IRC, Jabber, Mail.ru Agent, SMTP, Social Networks, Web Mail, Windows Messenger, and Yahoo Messenger.

If you select several protocols that have different access rights, under Action(s), the dialog box displays only those access rights that are common to all selected protocols.

11. Under **Action(s)**, specify which user actions are allowed or disallowed on protocols and which user actions are logged to the Shadow Log.

For detailed information on user rights that can be specified in Content-Aware Rules, see "<u>Content-Aware Rules for Access Control Operations</u>" and "<u>Content-Aware Rules for Shadow Copy Operations</u>."

#### 12. Click **OK**.
The rule you created is displayed under Rules in the lower-right pane of the Content-Aware Rules dialog box.

13. Click **OK** or **Apply** to apply the rule.

The users or groups to which the Content-Aware Rule applies are displayed under Content-Aware Rules in the console tree. When you select a user or group to which a Content-Aware Rule applies in the console tree, in the details pane you can view detailed information regarding this rule. This information includes the following:

- **Description** The name of the rule. By default, the rule has the same name as the specified content group.
- Type The type of the content analysis. Possible values: File Type Detection, Keywords, Pattern, Document Properties, and Complex. File Type Detection indicates that recognition and identification of files is based on their characteristic signatures. Keywords indicates that recognition and identification of data/files is based on the specified keywords or phrases.
   Pattern indicates that recognition and identification of data/files is based on the specified patterns of text described by Perl regular expressions.
   Document Properties indicates that recognition and identification of files is based on their properties. Complex indicates that recognition and identification of data/files is based on the specified content described by a Boolean expression.
- Action(s) Shows which user actions are allowed or disallowed on protocols and which user actions are logged to the Shadow Log.
- Applies To Possible values: Permissions, Shadowing, and Permissions, Shadowing. Permissions indicates that the rule applies to access control operations. Shadowing indicates that the rule applies to shadow copy operations. Permissions, Shadowing indicates that the rule applies to both access control and shadow copy operations.
- **Protocol(s)** The protocol(s) to which the rule applies.
- **Profile** Possible values: **Regular** and **Offline**. **Regular** indicates that the rule applies to client computers that are working online. **Offline** indicates that the rule applies to computers that are working offline. You can define different online vs. offline Content-Aware Rules for the same user or sets of users. For information about how to define offline Content-Aware Rules for protocols, see "<u>Managing Offline Content-Aware Rules for Protocols</u>."

## **Editing Content-Aware Rules**

You can modify the Content-Aware Rule properties such as Description, Applies To, Protocol(s), Actions.

### To edit a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

a) Open DeviceLock Service Settings Editor.

b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, right-click **Content-Aware Rules**, click **Manage**, and then do the following:
  - a) In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group for which you want to edit the rule. By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.
  - b) In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, select the rule you want to edit, and then click **Edit**.
    - OR -

Right-click the rule, and then click **Edit**.

- OR -

Under Protocols, expand Content-Aware Rules, and then do the following:

a) Under **Content-Aware Rules**, select the user or group for which you want to edit the rule.

*By selecting users or groups, you can view the Content-Aware Rules applied to them in the details pane.* 

b) In the details pane, right-click the rule you want to edit, and then click **Edit**. - OR -

In the details pane, double-click the rule you want to edit.

The Edit Rule dialog box appears.

- 4. In the **Edit Rule** dialog box, modify the rule properties as required to meet your needs.
- 5. Click **OK** to apply the changes.

## **Copying Content-Aware Rules**

You can perform a cut-and-paste operation, a copy-and-paste operation or a drag-and-drop operation to reuse existing Content-Aware Rules.

### To copy a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

a) Open DeviceLock Service Settings Editor.

b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage.
     OR -
  - Select **Content-Aware Rules**, and then click **Manage** on the toolbar.

The Content-Aware Rules dialog box appears.

4. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group to which the rule that you want to copy is applied.

By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.

5. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, right-click the rule you want to copy, and then click **Copy** or **Cut**.

The rule you cut or copy is automatically copied to the Clipboard.

You can use the CTRL+C, CTRL+X and CTRL+V key combinations to copy, cut and paste the rule. When you use the CTRL+X key combination to cut the rule, the rule will be cut only after you paste it.

To perform a drag-and-drop operation, select the rule and move it to the user or group to which you want to apply the copied rule.

6. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

7. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups to which you want to apply the copied rule, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules dialog box.

8. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the users or groups to which you want to apply the copied rule.

*You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.* 

9. In the lower-right pane of the **Content-Aware Rules** dialog box, right-click in the **Rules** pane and then click **Paste**.

The copied rule is displayed under Rules in the lower-right pane of the Content-Aware Rules dialog box. 10. Click **OK** or **Apply** to apply the copied rule.

## **Exporting and Importing Content-Aware Rules**

You can export all your current Content-Aware Rules to a .cwl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

### **To export Content-Aware Rules**

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Save.
     OR -
  - Select Content-Aware Rules, and then click Save 

     OR
  - Expand Content-Aware Rules, right-click any user or group to which the rule is applied, and then click Save.
     OR -
  - Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Save**.
    - OR -
  - Expand Content-Aware Rules, select any user or group to which the rule is applied, and then click Save I on the toolbar.
     OR -
  - Right-click **Content-Aware Rules**, and then click **Manage**. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, click **Save**.

The Save As dialog box appears.

- 4. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .cwl file.
- 5. In the **File name** box, type the file name you want.
- 6. Click Save.

When you export rules, they are saved in a file with a .cwl extension.

### To import Content-Aware Rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Load.
     OR -
  - Select Content-Aware Rules, and then click Load on the toolbar.
     OR -
  - Expand Content-Aware Rules, right-click any user or group to which the rule is applied, and then click Load.
     OR -
  - Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Load**.
    - OR -
  - Expand Content-Aware Rules select any user or group to which the rule is applied, and then click Load in the toolbar.
     OR -
  - Right-click **Content-Aware Rules**, and then click **Manage**. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, click **Load**.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open**.

You can import only one .cwl file at a time.

## **Undefining Content-Aware Rules**

If you deploy DeviceLock policies using DeviceLock Group Policy Manager or DeviceLock Service Settings Editor, in some situations you may want to prevent Content-Aware Rules from being applied to a specific group of client computers. To do so, you need to return the previously defined Content-Aware Rules to the unconfigured state. All undefined DeviceLock settings are ignored by client computers.

## **To undefine Content-Aware Rules**

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, right-click DeviceLock Settings or DeviceLock Service, and then click Load Service Settings to open the XML file with defined DeviceLock policies.
  - c) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, right-click **Content-Aware Rules**, and then click **Undefine**.

## **Deleting Content-Aware Rules**

You can delete individual Content-Aware Rules when they are no longer required.

### To delete a Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Expand **Content-Aware Rules**, right-click the user or group to which the rule is applied, and then click **Delete user**.

When you delete a user or group, the rule associated with this user or group is automatically deleted.

- OR -

- Expand Content-Aware Rules, and then select the user or group to which the rule is applied. In the details pane, right-click the rule associated with this user or group, and then click Delete.
   OR -
- Right-click **Content-Aware Rules**, and then click **Manage**. In the lower-left pane of the **Content-Aware Rules** dialog box, under **Users**, select the user or group to which the rule is applied. In the lower-right pane of the **Content-Aware Rules** dialog box, under **Rules**, select the rule, and then click **Delete** or right-click the rule, and then click **Delete**.

You can select multiple rules that you want to delete by holding down the SHIFT key or the CTRL key while clicking them.

# **Protocols (Regular Profile)**

DeviceLock allows you to control data that is transferred over different network protocols, thus enhancing protection against unwanted information disclosure and offering additional transport-level security. With the Protocols feature, you can define policies to selectively allow or block data/file transmission via specific protocols as well as shadow copy the transferred data. For flexibility, policies can be defined on a per-user or per-group basis.

DeviceLock provides control over the following protocols and Web applications:

• **FTP** (File Transfer Protocol) The Internet standard protocol for transferring files between computers.

Both active-mode and passive-mode FTP connections are supported. FTPS (FTP over SSL) is also supported. Both implicit and explicit FTPS connections are supported.

- HTTP (Hypertext Transfer Protocol) An application-level client/server protocol used to transfer information over the World Wide Web.
   HTTPS (SSL over HTTP) is also supported.
- ICQ/ AOL Messenger AOL's Open System for Communication in Realtime (OSCAR) protocol used by ICQ and AOL Instant Messenger (AIM).
   Both non-SSL and SSL connections are supported.
- **IRC** (Internet Relay Chat) An Internet standard protocol that supports interactive, real-time, text-based communications in established "chat rooms" on the Internet by means of IRC servers.

Both non-SSL and SSL connections are supported.

- **Jabber** An open, XML-based protocol for instant messaging. Both non-SSL and SSL connections are supported.
- **Mail.ru Agent** An instant messaging program created by Mail.ru.
- SMTP (Simple Mail Transfer Protocol) An Internet standard protocol used for exchanging e-mail messages between SMTP servers on the Internet.
   Extended SMTP (ESMTP) is also supported. Both non-SSL and SSL connections are supported.
- Social Networks Controls communication with social networking sites. The following social networking sites are supported: Facebook, Google+, LinkedIn, LiveJournal, MeinVZ, Myspace, Odnoklassniki, SchuelerVZ, StudiVZ, Tumblr, Twitter, Vkontakte, XING.

**Note:** SSL traffic on social networking sites is controlled as generic (non-SSL) traffic.

- **Telnet** The Internet standard protocol for remote terminal connection service.
- **Web Mail** Controls Web-based mail communication. The following Web-based e-mail services are supported: AOL Mail, Gmail, GMX Mail, Hotmail, Mail.ru, Rambler Mail, Web.de, Yahoo! Mail, and Yandex Mail.

Both non-SSL and SSL connections are supported.

- **Windows Messenger** Microsoft Notification Protocol (MSNP), the underlying protocol used by Windows Live Messenger and Windows Messenger.
- **Yahoo Messenger** The underlying network protocol used by the Yahoo! Messenger instant messaging client for Yahoo!

**Note:** The SSL protocol is used in the Protocols White List to allow applications with embedded SSL certificates to connect to their servers.

You can manage protocol security policies by using DeviceLock Management Console, Service Settings Editor, or DeviceLock Group Policy Manager. You can also use the Report Permissions/Auditing plug-in in DeviceLock Enterprise Server to view and change security policies defined for protocols. For more information, see "<u>Report Permissions/Auditing</u>."

## **Managing Permissions for Protocols**

To govern the exchange of information at the transport level, configure access to communications protocols by setting appropriate permissions. These permissions specify who can gain access to which protocols and what level of access users have. Permissions can be set on a per-user or per-group basis.

The following	table describes	access rights	available fo	r permissions	associated v	with
protocols.						

PROTOCOL	ACCESS RIGHTS
FTP	Generic: Send/Receive Data The right to connect to an FTP server, send and receive protocol data, download files from an FTP server.
	Generic: Outgoing Files The right to upload files to an FTP server.
	<b>SSL: Send/Receive Data</b> The right to connect to an FTP server, send and receive protocol data, download files from an FTP server using FTPS.
	SSL: Outgoing Files The right to upload files to an FTP server using FTPS.
НТТР	<b>Generic: Send/Receive Data</b> The right to connect to a Web server, send and receive protocol data, web pages and objects on web pages (such as scripts, Flash files, JPEG, PNG, and GIF images, etc.).
	Generic: POST Requests The right to submit Web form data to a Web server using HTTP.
	Generic: Outgoing Files The right to upload files to a Web server using HTTP.
	<b>SSL: Send/Receive Data</b> The right to connect to a Web server, send and receive protocol data, web pages and objects on web pages (such as scripts, Flash files, JPEG, PNG, and GIF images, etc.) using HTTPS.
	<b>SSL: POST Requests</b> The right to submit Web form data to a Web server using HTTPS.
	SSL: Outgoing Files The right to upload files to a Web server using HTTPS.
ICQ/AOL	Generic: Send/Receive Data The right to connect to the ICQ and AOL Instant

PROTOCOL	ACCESS RIGHTS
Messenger	Messenger server and receive instant messages.
	<b>Generic: Outgoing Messages</b> The right to send instant messages. It does not control file transfers.
	<b>SSL: Send/Receive Data</b> The right to connect to the ICQ and AOL Instant Messenger server and receive instant messages using SSL.
	<b>SSL: Outgoing Messages</b> The right to send instant messages using SSL. It does not control file transfers.
IRC	Generic: Send/Receive Data The right to connect to an IRC server and receive instant messages.
	Generic: Outgoing Messages The right to send instant messages. It does not control file transfers.
	SSL: Send/Receive Data The right to connect to an IRC server using SSL.
	<b>SSL: Outgoing Messages</b> The right to send instant messages using SSL. It does not control file transfers.
Jabber	Generic: Send/Receive Data The right to connect to a Jabber server and receive instant messages.
	Generic: Outgoing Messages The right to send instant messages. It does not control file transfers.
	SSL: Send/Receive Data The right to connect to a Jabber server using SSL.
	<b>SSL: Outgoing Messages</b> The right to send instant messages using SSL. It does not control file transfers.
Mail.ru Agent	Generic: Send/Receive Data The right to connect Mail.ru Agent to the Mail.ru server and receive instant messages.
	<b>Generic: Outgoing Messages</b> The right to send instant messages. It does not control file transfers.
SMTP	Generic: Send/Receive Data The right to connect to an SMTP server and to send and receive protocol data.
	<b>Generic: Outgoing</b> Messages The right to send e-mail messages without attachments.
	Generic: Outgoing Files The right to send e-mail attachments.
	<b>SSL: Send/Receive Data</b> The right to connect to an SMTP server and to send and receive protocol data using SSL.
	SSL: Outgoing Messages The right to send e-mail messages without attachments using SSL.
	SSL: Outgoing Files The right to send e-mail attachments using SSL.
Social Networks	Generic: Send/Receive Data The right to have view access to a social networking site.
	<b>Generic: Outgoing Messages</b> The right to send messages, comments, posts, etc.
	Generic: Outgoing Files The right to upload media and file content to a social networking site.

PROTOCOL	ACCESS RIGHTS		
Telnet	Generic: Send/Receive Data The right to connect to a Telnet server and to send and receive protocol data.		
Web Mail	Generic: Send/Receive Data The right to access Webmail and read e-mail.		
	Generic: Outgoing Messages The right to send e-mail messages without attachments.		
	Generic: Outgoing Files The right to send e-mail attachments.		
	SSL: Send/Receive Data The right to access Webmail and read e-mail using SSL.		
	SSL: Outgoing Messages The right to send e-mail messages without attachments using SSL.		
	SSL: Outgoing Files The right to send e-mail attachments using SSL.		
Windows Messenger	Generic: Send/Receive Data The right to connect to the Windows Messenger server.		
	<b>Generic: Outgoing Messages</b> The right to send instant messages. It does not control file transfers.		
Yahoo Messenger	Generic: Send/Receive Data The right to connect to the Yahoo Messenger server.		
	<b>Generic: Outgoing Messages</b> The right to send instant messages. It does not control file transfers.		

**Note:** You can define different online vs. offline permissions on protocols for the same user or sets of users. Online permissions (Regular Profile) apply to client computers that are working online. Offline permissions (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define offline permissions for protocols, see "Managing Offline Permissions for Protocols."

You can set the default permissions on protocols for both types of profiles (Regular Profile and Offline Profile). The default permissions are assigned to the Administrators and Everyone accounts. The following table lists access rights granted to these accounts by default.

ACCOUNT/ PROTOCOL	ADMINISTRATORS	EVERYONE
FTP	Generic: Send/Receive Data, Outgoing Files SSL: Send/Receive Data, Outgoing Files	Generic: Send/Receive Data SSL: Send/Receive Data
НТТР	Generic: Send/Receive Data, Outgoing Files SSL: Send/Receive Data, Outgoing	Generic: Send/Receive Data SSL: Send/Receive Data

ACCOUNT/ PROTOCOL	ADMINISTRATORS	EVERYONE
	Files	
ICQ/AOL Messenger	Generic: Send/Receive Data, Outgoing Messages	Generic: Send/Receive Data, Outgoing Messages
	SSL: Send/Receive Data, Outgoing Messages	SSL: Send/Receive Data, Outgoing Messages
IRC	Generic: Send/Receive Data, Outgoing Messages	Generic: Send/Receive Data, Outgoing Messages
	SSL: Send/Receive Data, Outgoing Messages	SSL: Send/Receive Data, Outgoing Messages
Jabber	Generic: Send/Receive Data, Outgoing Messages	Generic: Send/Receive Data, Outgoing Messages
	SSL: Send/Receive Data, Outgoing Messages	SSL: Send/Receive Data, Outgoing Messages
Mail.ru Agent	Generic: Send/Receive Data, Outgoing Messages	Generic: Send/Receive Data, Outgoing Messages
SMTP	Generic: Send/Receive Data, Outgoing Messages, Outgoing Files	Generic: Send/Receive Data, Outgoing Messages
	SSL: Send/Receive Data, Outgoing Messages, Outgoing Files	SSL: Send/Receive Data, Outgoing Messages
Social Networks	Generic: Send/Receive Data, Outgoing Messages, Outgoing Files	Generic: Send/Receive Data, Outgoing Messages
Telnet	Generic: Send/Receive Data	Generic: Send/Receive Data
Web Mail	Generic: Send/Receive Data, Outgoing Messages, Outgoing Files	Generic: Send/Receive Data, Outgoing Messages
	SSL: Send/Receive Data, Outgoing Messages, Outgoing Files	SSL: Send/Receive Data, Outgoing Messages
Windows Messenger	Generic: Send/Receive Data, Outgoing Messages	Generic: Send/Receive Data, Outgoing Messages
Yahoo Messenger	Generic: Send/Receive Data, Outgoing Messages	Generic: Send/Receive Data, Outgoing Messages

Managing online (regular) permissions for protocols involves the following tasks:

- Setting and editing permissions
- Undefining permissions

Online permissions for protocols can have one of the following states:

STATE	DESCRIPTION
Not Configured	Indicates that permissions on a protocol are not set.

STATE	DESCRIPTION		
Configured	Indicates that permissions on a protocol are set.		
Full Access	Indicates that full access rights are granted to the Everyone account.		
No Access	<ul> <li>Indicates one of the following:</li> <li>The Everyone account has No Access permissions and is the only account assigned to a protocol. No Access permissions assigned to the Everyone account take priority over permissions assigned to other accounts.</li> <li>All users and groups assigned to a protocol have No Access permissions.</li> <li>All users and groups assigned to a protocol are removed.</li> </ul>		

## **Setting and Editing Permissions**

### To set and edit permissions

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under Protocols, select Permissions.

When you select Permissions in the console tree, in the details pane you can view protocols for which you can set permissions. In the details pane, you can also view the current state of online (regular) permissions for each protocol in the Regular column.

- 4. In the details pane, do one of the following:
  - Right-click the protocol for which you want to set or edit permissions, and then click **Set Permissions**.
    - OR -
  - Select the protocol for which you want to set or edit permissions, and then click Set Permissions & on the toolbar.

You can select several protocols for which you want to set the same permissions by holding down the SHIFT key or the CTRL key while clicking them

**Note:** When selecting several protocols that have different access rights, consider the following:

The **Permissions** dialog box displays only those access rights that are common to all selected protocols.

If all access rights displayed in the **Permissions** dialog box are allowed for the specified users, these users will have full access to the selected protocols.

If all access rights displayed in the **Permissions** dialog box are denied for the specified users, these users will have no access to the selected protocols.

Some access rights depend on other rights. If you grant a right that requires another right, the required right is granted automatically. For example, if you grant only the **Generic: Outgoing Files** right for the Social Networks and Web Mail protocols, the following rights are granted automatically: **Generic: Send/Receive Data, Generic: Outgoing Messages**, **Generic: Outgoing Files**.



The Permissions dialog box appears.

5. In the **Permissions** dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS
To set the default permissions	<ul> <li>In the upper-left pane of the dialog box, under Users, click Set Default.</li> </ul>
	The default permissions are assigned to the Administrators, and Everyone accounts. For information about which permissions are set for these accounts by default, see " <u>Managing Permissions for</u> <u>Protocols</u> ."
To set permissions for an additional user or group	1. In the upper-left pane of the dialog box, under <b>Users</b> , click <b>Add</b> .
	The Select Users or Groups dialog box appears.
	<ol> <li>In the Select Users or Groups dialog box, in the Enter the object names to select box, type the name of the user or group, and then click OK.</li> </ol>
	The users and groups that you added are displayed under Users

TO DO THIS	FOLLOW THESE STEPS		
	<ul> <li>in the upper-left pane of the Permissions dialog box.</li> <li>3. In the upper-left pane of the <b>Permissions</b> dialog box, under <b>Users</b>, select the user or group.</li> </ul>		
	You can select multiple users and/ or groups by holding down the SHIFT key or the CTRL key while clicking them.		
	<ol> <li>In the lower-left pane of the <b>Permissions</b> dialog box, under User's Rights, select or clear the Allow check box next to the appropriate access rights.</li> </ol>		
	In the right pane of the Permissions dialog box, you can set day and time restrictions that narrow user access to the specified protocol(s). Use the left mouse button to select days and hours when the selected user or group will have access to the specified protocol(s). Use the right mouse button to mark days and hours when the selected user or group will not have access to the specified protocol(s).		
To change permissions for	<ol> <li>In the upper-left pane of the dialog box, under Users, select the user or group.</li> </ol>		
an existing user or group	<ol> <li>In the lower-left pane of the dialog box, under User's Rights, select or clear the Allow check box next to the appropriate access rights.</li> </ol>		
To remove an existing user or group and permissions	<ul> <li>In the upper-left pane of the dialog box, under Users, select the user or group, and then click Delete or press the DELETE key.</li> </ul>		

6. Click OK or Apply.

## **Undefining Permissions**

If you deploy DeviceLock policies using DeviceLock Group Policy Manager or DeviceLock Service Settings Editor, in some situations you may want to prevent some or all of the previously set permissions for protocols from being applied to a specific group of client computers. To do so, you need to return the previously set permissions to the unconfigured state. All undefined DeviceLock settings are ignored by client computers.

## To undefine permissions

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, right-click DeviceLock Settings or DeviceLock Service, and then click Load Service Settings to open the XML file with defined DeviceLock policies.
  - c) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.

## 2. Expand **Protocols**.

3. Under **Protocols**, select **Permissions**.

When you select Permissions in the console tree, in the details pane you can view protocols for which you can set permissions.

4. In the details pane, right-click the protocol whose permissions you want to undefine, and then click **Undefine**.

You can undefine permissions for multiple protocols at the same time. To do this, do the following:

- a) In the details pane, select multiple protocols by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Undefine**.

## Managing Audit and Shadowing Rules for Protocols

DeviceLock provides the capability to audit and shadow copy data/file transfers via different protocols. Auditing and shadow copying are used to monitor and record security-critical data transfer operations. Regular analysis of log data is an effective way to detect and trace misuse of sensitive information and data breach incidents caused by data loss or theft.

For auditing and shadow copying at the transport level, DeviceLock uses two types of logging: Audit Logs and Shadow Logs. The Audit Log is used to audit access to protocols and track what individual users do. Audit data can be written to the Windows Event Log, to the DeviceLock proprietary log, or both. To define what log should be used, set the <u>Audit log</u> type parameter in Service Options. To view audit log data, use either <u>DeviceLock Service</u> <u>Audit Log Viewer</u> or <u>DeviceLock Enterprise Server Audit Log Viewer</u>.

The Shadow Log is used to store a full copy of data/files transferred via specified protocols. To view shadow log data, use either <u>DeviceLock Service Shadow Log Viewer</u> or <u>DeviceLock Enterprise Server Shadow Log Viewer</u>.

Auditing and shadow copying of data transferred via specified protocols are enabled by defining audit and shadowing rules. Each rule associated with a protocol specifies users or groups the rule applies to and appropriate audit/shadowing rights which determine which user actions to audit/shadow copy.

Audit events logged include a variety of information such as the event type, the date and time of the event, the associated protocol, the user associated with this event, process information and event-specific information.

The following table provides summary information on audit and shadowing rights that can be specified in rules and describes event-specific information that is written to the log.

PROTOCOL	AUDIT/SHADOWING RIGHTS
FTP	Audit: Connection – Enables audit logging of user attempts to connect to an FTP site.

PROTOCOL	AUDIT/SHADOWING RIGHTS		
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.		
	Audit: Incoming Files – Enables audit logging of user attempts to download a file from an FTP site.		
	The Incoming File action, the absolute path and complete name of the file (for example, ftp://myftp/myfile.doc), the IP address with the port number and the name of the host are written to the log.		
	Audit: Outgoing Files – Enables audit logging of user attempts to upload a file to an FTP site.		
	The Outgoing File action, the absolute path and complete name of the file (for example, ftp://myftp/myfile.doc), the IP address with the port number and the name of the host are written to the log.		
	Shadowing: Incoming Files – Enables shadow copying of files downloaded from an FTP site.		
	Shadow copies of downloaded files are written to the log.		
	Shadowing: Outgoing Files – Enables shadow copying of files uploaded to an FTP site.		
	Shadow copies of uploaded files are written to the log.		
НТТР	Audit: Connection – Enables audit logging of user attempts to open a web page.		
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.		
	<b>Note:</b> When this right is enabled, numerous Connection events are recorded in the Audit Log each time a user attempts to open a web page. This happens because a web page often requests resources (such as images, scripts, etc.) from other hosts.		
	Audit: Incoming Data – Enables audit logging of web pages and objects on web pages: scripts, Flash files (up to 1.5 MB in size), images (up to 512 KB in size), text (up to 200 KB in size), etc.		
	The Incoming Data action, the URL of the web page and objects on the web page, the IP address with the port number and the name of the host are written to the log.		
	Audit: Incoming Files – Enables audit logging of user attempts to download a file from a Web site.		
	The Incoming File action, the absolute path and complete name of the file (for example, http://domain/path/myfile.doc), the IP address with the port number and the name of the host are written to the log.		
	Audit: Outgoing Data – The Outgoing Data content type contains no data. This right enables audit logging of blocked user attempts to open a web page, if the Audit Denied option is set for the protocol.		
	The Outgoing Data action, the URL of the web page and objects on the web page, the IP address with the port number and the name of the host are written to the log.		
	Audit: POST Requests – Enables audit logging of user attempts to submit Web		

PROTOCOL	AUDIT/SHADOWING RIGHTS
	form data to a Web site.
	The POST Request action and the URL of the script that sent the POST request are written to the log.
	Audit: Outgoing Files – Enables audit logging of user attempts to upload a file to a Web site.
	The Outgoing File action, the absolute path and complete name of the file (for example, http://domain/path/myfile.doc), the IP address with the port number and the name of the host are written to the log.
	<b>Shadowing: Incoming Data</b> – Enables shadow copying of web pages and objects on web pages: scripts, Flash files (up to 1.5 MB in size), images (up to 512 KB in size), text (up to 200 KB in size), etc.
	Shadow copies of web pages and their constituent components are written to the log.
	Shadowing: Incoming Files – Enables shadow copying of files downloaded from a Web site.
	Shadow copies of downloaded files are written to the log.
	Shadowing: Outgoing Data – This right has no impact on shadow copying.
	Shadowing: POST Requests – Enables shadow copying of data entered into Web forms.
	Shadow copies of data entered into Web forms are written to the log.
	Shadowing: Outgoing Files – Enables shadow copying of files uploaded to a Web site.
	Shadow copies of uploaded files are written to the log.
ICQ/AOL Messenger	Audit: Connection – Enables audit logging of user attempts to connect to the ICQ and AOL Instant Messenger server.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Incoming Messages, Outgoing Messages – Enables audit logging of user attempts to send and receive instant messages.
	The Chat action, IDs of all IM participants, the IP address with the port number and the name of the host are written to the log. The ID of the local participant precedes the ID of a remote participant.
	Shadowing: Incoming Messages – Enables shadow copying of received instant messages.
	Shadow copies of received instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all received messages.
	Shadowing: Outgoing Messages – Enables shadow copying of sent instant messages.
	Shadow copies of sent instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is. 30 minutes after the last active exchange in the chat window) or if the user

PROTOCOL	AUDIT/SHADOWING RIGHTS
	quits the instant messenger. It contains an exact record of all sent messages.
IRC	Audit: Connection – Enables audit logging of user attempts to connect to an IRC server.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Incoming Messages, Outgoing Messages – Enables audit logging of user attempts to send and receive instant messages.
	The Chat action, IDs of all IM participants, the IP address with the port number and the name of the host are written to the log. The ID of the local participant precedes the ID of a remote participant.
	Shadowing: Incoming Messages – Enables shadow copying of received instant messages.
	Shadow copies of received instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all received messages.
	Shadowing: Outgoing Messages – Enables shadow copying of sent instant messages.
	Shadow copies of sent instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all sent messages.
Jabber	Audit: Connection – Enables audit logging of user attempts to connect to a Jabber server.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Incoming Messages, Outgoing Messages – Enables audit logging of user attempts to send and receive instant messages.
	The Chat action, IDs of all IM participants, the IP address with the port number and the name of the host are written to the log. The ID of the local participant precedes the ID of a remote participant.
	Shadowing: Incoming Messages – Enables shadow copying of received instant messages.
	Shadow copies of received instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all received messages.
	Shadowing: Outgoing Messages – Enables shadow copying of sent instant messages.
	Shadow copies of sent instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all sent messages.

PROTOCOL	AUDIT/SHADOWING RIGHTS
Mail.ru Agent	Audit: Connection – Enables audit logging of user attempts to connect Mail.ru Agent to the Mail.ru server.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Incoming Messages, Outgoing Messages – Enables audit logging of user attempts to send and receive instant messages.
	The Chat action, IDs of all IM participants, the IP address with the port number and the name of the host are written to the log. The ID of the local participant precedes the ID of a remote participant.
	Shadowing: Incoming Messages – Enables shadow copying of received instant messages.
	Shadow copies of received instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all received messages.
	Shadowing: Outgoing Messages – Enables shadow copying of sent instant messages.
	Shadow copies of sent instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all sent messages.
SMTP	Audit: Connection – Enables audit logging of user attempts to connect to an SMTP server.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Outgoing Messages, Outgoing Files – Enables audit logging of user attempts to send an e-mail message with or without attachments.
	The Outgoing Message action, the e-mail address of the sender and recipients, the IP address with the port number and the name of the host are written to the log. The sender address precedes recipient addresses (sender=>recipient1, recipient2).
	<b>Shadowing: Outgoing Messages, Outgoing Files</b> – Enables shadow copying of sent e-mail messages with or without attachments.
	Shadow copies of sent e-mail messages with or without attachments are written to the log as .eml files. You can, for example, open .eml files in Microsoft Outlook Express, in Windows Mail, and in Mozilla Thunderbird.
Social Networks	Audit: Connection – Enables audit logging of user attempts to connect to a social networking site.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Outgoing Messages – Enables audit logging of user attempts to send messages, comments, posts, etc.

PROTOCOL	AUDIT/SHADOWING RIGHTS
	The Outgoing Message action and the following information ( <site_name>_<content_name>_<recipient id="">) are written to the log. Recipient IDs are written to the log only if users attempt to send messages. Recipient IDs are written in a number format.</recipient></content_name></site_name>
	Audit: Outgoing Files – Enables audit logging of user attempts to upload media and file content to a social networking site.
	<i>The Outgoing File action and the following information (<site_name>_<file_name>) are written to the log.</file_name></site_name></i>
	Shadowing: Outgoing Messages – Enables shadow copying of sent messages, comments, posts, etc.
	Shadow copies of sent messages, comments, etc. are written to the log.
	Shadowing: Outgoing Files – Enables shadow copying of files uploaded to a social networking site.
	Shadow copies of uploaded files are written to the log.
Telnet	Audit: Connection – Enables audit logging of user attempts to connect to a Telnet site.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log
Web Mail	Audit: Connection – Enables audit logging of user attempts to access Webmail.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Outgoing Messages, Outgoing Files – Enables audit logging of user attempts to send an e-mail message with or without attachments.
	The Outgoing Message action, the name of the e-mail provider (such as Yahoo, Gmail, Hotmail, etc.), the e-mail address of the sender and recipients, the IP address with the port number and the name of the host are written to the log. The sender address precedes recipient addresses (sender=>recipient1, recipient2).
	Shadowing: Outgoing Messages, Outgoing Files – Enables shadow copying of sent e-mail messages with or without attachments.
	Shadow copies of sent e-mail messages with or without attachments are written to the log as .eml files. You can, for example, open .eml files in Microsoft Outlook Express, in Windows Mail, and in Mozilla Thunderbird.
	<b>Note:</b> Webmail services automatically save drafts of messages. DeviceLock handles saving a draft as sending a message.
Windows Messenger	Audit: Connection – Enables audit logging of user attempts to connect to the Windows Messenger server.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Incoming Messages, Outgoing Messages - Enables audit logging of

PROTOCOL	AUDIT/SHADOWING RIGHTS
	user attempts to send and receive instant messages.
	The Chat action, the ID of the local participant, the IP address with the port number and the name of the host are written to the log.
	Shadowing: Incoming Messages – Enables shadow copying of received instant messages.
	Shadow copies of received instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all received messages.
	Shadowing: Outgoing Messages – Enables shadow copying of sent instant messages.
	Shadow copies of sent instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all sent messages.
Yahoo Messenger	Audit: Connection – Enables audit logging of user attempts to connect to the Yahoo Messenger server.
	The Connection action, the IP address with the port number and the name of the host, the name of the protocol are written to the log. If IP address to host name resolution fails, the host name is not written to the log.
	Audit: Incoming Messages, Outgoing Messages – Enables audit logging of user attempts to send and receive instant messages.
	The Chat action, IDs of all IM participants, the IP address with the port number and the name of the host are written to the log. The ID of the local participant precedes the ID of a remote participant.
	Shadowing: Incoming Messages – Enables shadow copying of received instant messages.
	Shadow copies of received instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all received messages.
	Shadowing: Outgoing Messages – Enables shadow copying of sent instant messages.
	Shadow copies of sent instant messages are written to the log as .txt files. A shadow copy of messages is written to the log after 30 minutes of inactivity (that is, 30 minutes after the last active exchange in the chat window) or if the user quits the instant messenger. It contains an exact record of all sent messages.

**Note:** You can define different online vs. offline audit and shadowing rules for the same user or sets of users. Online audit and shadowing rules (Regular Profile) apply to client computers that are working online. Offline audit and shadowing rules (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define offline audit and shadowing rules for protocols, see "Managing Offline Audit and Shadowing Rules for Protocols."

GROUP/ PROTOCOL	USERS	EVERYONE
FTP	Audit: Connection	Audit: Connection
	Audit: Incoming Files	Audit: Incoming Files
	Audit: Outgoing Files	Audit: Outgoing Files
НТТР	Audit: Connection	Audit: Connection
	Audit: Incoming Data	Audit: Incoming Data
	Audit: Incoming Files	Audit: Incoming Files
	Audit: Outgoing Data	Audit: Outgoing Data
	Audit: POST Requests	Audit: POST Requests
	Audit: Outgoing Files	Audit: Outgoing Files
ICQ/AOL	Audit: Connection	Audit: Connection
Messenger	Audit: Incoming Messages	Audit: Incoming Messages
	Audit: Outgoing Messages	Audit: Outgoing Messages
IRC	Audit: Connection	Audit: Connection
	Audit: Incoming Messages	Audit: Incoming Messages
	Audit: Outgoing Messages	Audit: Outgoing Messages
Jabber	Audit: Connection	Audit: Connection
	Audit: Incoming Messages	Audit: Incoming Messages
	Audit: Outgoing Messages	Audit: Outgoing Messages
Mail.ru Agent	Audit: Connection	Audit: Connection
	Audit: Incoming Messages	Audit: Incoming Messages
	Audit: Outgoing Messages	Audit: Outgoing Messages
SMTP	Audit: Connection	Audit: Connection
	Audit: Outgoing Messages	Audit: Outgoing Messages
	Audit: Outgoing Files	Audit: Outgoing Files
Social Networks	Audit: Connection	Audit: Connection
	Audit: Outgoing Messages	Audit: Outgoing Messages
	Audit: Outgoing Files	Audit: Outgoing Files
Telnet	Audit: Connection	Audit: Connection
Web Mail	Audit: Connection	Audit: Connection
	Audit: Outgoing Messages	Audit: Outgoing Messages

You can define the default audit and shadowing rules for protocols for both types of profiles (Regular Profile and Offline Profile). The default rules apply to the Users and Everyone groups. The following table lists rights granted to these groups by default.

GROUP/ PROTOCOL	USERS	EVERYONE
	Audit: Outgoing Files	Audit: Outgoing Files
Windows Messenger	Audit: Connection Audit: Incoming Messages Audit: Outgoing Messages	Audit: Connection Audit: Incoming Messages Audit: Outgoing Messages
Yahoo Messenger	Audit: Connection Audit: Incoming Messages Audit: Outgoing Messages	Audit: Connection Audit: Incoming Messages Audit: Outgoing Messages

Managing online (regular) audit and shadowing rules for protocols involves the following tasks:

- Defining and editing audit and shadowing rules
- Undefining audit and shadowing rules

Online audit and shadowing rules for a protocol can have one of the following states:

STATE	DESCRIPTION
Not Configured	Indicates that audit and shadowing rules are not defined for a protocol.
Configured	Indicates that audit and shadowing rules are defined for a protocol.
No Audit	<ul> <li>Indicates one of the following:</li> <li>Audit rights are not set for all of the users and groups specified in audit and shadowing rules for a protocol.</li> <li>All users and groups specified in audit and shadowing rules for a protocol are removed.</li> <li>The Everyone account has no Audit and Shadowing rights and is the only account specified in audit and shadowing rules for a protocol.</li> </ul>

## **Defining and Editing Audit and Shadowing Rules**

### To define and edit audit and shadowing rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

a) Open Group Policy Object Editor.

- b) In the console tree, expand Computer Configuration, and then expand DeviceLock.
- 2. Expand Protocols.
- 3. Under **Protocols**, select **Auditing & Shadowing**.

When you select Auditing & Shadowing in the console tree, in the details pane you can view protocols for which you can define audit and shadowing rules. In the details pane you can also view the current state of online rules for each protocol in the Regular column.

- 4. In the details pane, do one of the following:
  - Right-click the protocol for which you want to define or edit rules, and then click Set Auditing & Shadowing.
    - OR -

- Select the protocol for which you want to define or edit rules, and then click • Set Auditing & Shadowing 🍻 on the toolbar. - OR -
- Double-click the protocol for which you want to define or edit rules. •

The Auditing & Shadowing dialog box appears.



5. In the **Auditing & Shadowing** dialog box, do the following:

To define the default audit       1. In the upper-left area of the dialog box, specify which events written to the Audit Log. Select the Audit Allowed check box audit successful attempts to gain access to a protocol. Select	TO DO THIS	FOLLOW THESE STEPS
rules       Audit Denied check box to audit unsuccessful attempts to gate access to a protocol.         2       In the upper left page of the dialog how under Upper click S	To define the default audit and shadowing rules	<ol> <li>In the upper-left area of the dialog box, specify which events are written to the Audit Log. Select the Audit Allowed check box to audit successful attempts to gain access to a protocol. Select the Audit Denied check box to audit unsuccessful attempts to gain access to a protocol.</li> <li>In the upper left page of the dialog box, upder Upper click Set</li> </ol>

TO DO THIS	FOLLOW THESE STEPS
	Default.
	The default audit and shadowing rules apply to the Users and Everyone groups. For information about which Audit and Shadowing rights are set for these accounts by default, see " <u>Managing Audit and Shadowing Rules for Protocols.</u> "
To define audit and shadowing rules for an additional user or group	<ol> <li>In the upper-left area of the dialog box, specify which events are written to the audit log. Select the <b>Audit Allowed</b> check box to audit successful attempts to gain access to a protocol. Select the <b>Audit Denied</b> check box to audit unsuccessful attempts to gain access to a protocol.</li> </ol>
5 1	2. In the upper-left pane of the dialog box, under <b>Users</b> , click <b>Add</b> .
	The Select Users or Groups dialog box appears.
	<ol> <li>In the Select Users or Groups dialog box, in the Enter the object names to select box, type the name of the user or group, and then click OK.</li> </ol>
	The users and groups that you added are displayed under Users in the upper-left pane of the Auditing & Shadowing dialog box.
	<ol> <li>In the upper-left pane of the Auditing &amp; Shadowing dialog box, under Users, select the user or group.</li> </ol>
	You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.
	<ol> <li>In the lower-left pane of the Auditing &amp; Shadowing dialog box, under User's Rights, select or clear the Allow check box next to the appropriate rights.</li> </ol>
	In the right pane of the Auditing & Shadowing dialog box, you can specify days and hours (for example, from 7 AM to 5 PM Monday through Friday) when the rule for the selected user or group will or will not be active. Use the left mouse button to select days and hours when the rule is active (audit time). Use the right mouse button to mark days and hours when the rule is not active (non-audit time).
To change audit and	<ol> <li>In the upper-left pane of the dialog box, under Users, select the user or group.</li> </ol>
shadowing rules for an existing user or group	<ol> <li>In the lower-left pane of the dialog box, under User's Rights, select or clear the Allow check box next to the appropriate rights.</li> </ol>
To remove an existing user or	<ul> <li>In the upper-left pane of the dialog box, under Users, select the user or group, and then click Delete or press the DELETE key.</li> </ul>
group and rules	When you remove a user or group, any rules for that user or group will also be removed.

### 6. Click **OK** or **Apply**.

## **Undefining Audit and Shadowing Rules**

If you deploy DeviceLock policies using DeviceLock Group Policy Manager or DeviceLock Service Settings Editor, in some situations you may want to prevent audit and shadowing rules defined for a particular protocol or protocols from being applied to a specific group of client computers. To do so, you need to return the previously defined rules to the unconfigured state. All undefined DeviceLock settings are ignored by client computers.

### To undefine audit and shadowing rules

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, right-click DeviceLock Settings or DeviceLock Service, and then click Load Service Settings to open the XML file with defined DeviceLock policies
  - c) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuratio**n, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, select **Auditing & Shadowing**.

When you select Auditing & Shadowing in the console tree, in the details pane you can view protocols for which you can define audit and shadowing rules.

4. In the details pane, right-click the protocol whose rules you want to undefine, and then click **Undefine**.

You can undefine rules for multiple protocols at the same time. To do this, do the following:

- a) In the details pane, select multiple protocols by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Undefine**.

## **Managing Protocols White List**

The Protocols White List lets you selectively allow network communication over any supported protocol regardless of existing protocol blocking settings. The white list is most effective in "least privilege" scenarios when you block all protocol traffic and then specifically authorize only what is required for employees to perform their daily job duties.

For example, suppose that you deny all users access to the SMTP and Web Mail protocols, and then use the white list to let certain users send mail to specific e-mail addresses so that the users can perform their job tasks. By applying these security policies, you can minimize potential risks of data leakage, theft, and misuse.

**Note:** Audit and shadow copying are not performed for data transfers allowed by the Protocols White List while whitelisted connections are audited.

The white list consists of rules associated with the specified protocol. Each rule specifies users or groups the rule applies to and contains a set of parameters associated with it. These parameters fall into two categories:

- General parameters that apply to all protocols
- Protocol-specific parameters.

The following table describes general parameters for a white list rule.

PARAMETER	DESCRIPTION
Protocol	Specifies the protocol the rule applies to.
Description	Specifies the name of the rule.

The following table describes protocol-specific parameters for a white list rule.

PARAMETER	DESCRIPTION
Hosts:	Applies to the FTP, HTTP, ICQ/AOL Messenger, IRC, Jabber, Mail.ru Agent, SMTP, SSL, Telnet, Windows Messenger, and Yahoo Messenger protocols.
	Specifies a list of allowed hosts for this rule. If this list is specified, these hosts will not be blocked.
	<ul> <li>Hosts may be specified in any of the following formats:</li> <li>DNS name (for example, www.example.com). You can use the asterisk (*) wildcard character in DNS names (for example, *.example.com denotes that the host name is any server whose name ends in the specified name).</li> </ul>
	<b>Caution:</b> Adding host names with wildcards to the white list for all protocols except HTTP does not guarantee that the white list rule will work as expected.
	Because DeviceLock uses the local Hosts file for host name resolution, a malicious user with local administrator rights can modify the Hosts file as required to bypass DeviceLock security policies. For example, if the white list allows HTTP access to gmail.com, a malicious user with local administrator rights can gain access to unauthorized www.ru by adding the " <b>194.87.0.50</b> gmail.com" entry to the Hosts file. In order to minimize security risks, we recommend that you specify IP addresses instead of host names.
	<ul> <li>IP address (for example, 12.13.14.15). You can specify a range of IP addresses separated by a dash (-) (for example, 12.13.14.18-12.13.14.28). You can also specify the subnet mask for the IP address using the following format: IP address/subnet mask width in bits (for example, 3.4.5.6/16).</li> </ul>
	Multiple hosts must be separated by a comma (,) or semicolon (;). You can also press ENTER after each entry.
	You can specify multiple hosts in different formats described above (for example, www.microsoft.com; 12.13.14.15, 12.13.14.18-12.13.14.28).
	Note: When adding hosts to the white list, consider the following:
	If objects (images, scripts, video, Flash files, ActiveX, etc.) on a web page are downloaded from other hosts, you must add those hosts to the white list to load the

PARAMETER	DESCRIPTION
	web page correctly.
	If you specify hosts and do not specify ports, the hosts can be accessed through all available ports.
	An application with an embedded SSL certificate (for example, Microsoft Office Communicator, Dropbox, iTunes Google contacts synchronization module, etc.) will fail to connect to its server when the NetworkLock module is active. The NetworkLock module becomes active when you define settings for protocols. To solve this issue, add the server host to the white list for SSL. You can use TcpView to look up the server host. Whitelisting a server host causes all SSL traffic between an application and the specified server host to bypass access control, audit, shadow copying and content filtering.
Ports	Applies to the FTP HTTP ICO/AOI Messenger IPC Jabber Mail ru Agent SMTP
FOILS.	SSL, Telnet, Windows Messenger, and Yahoo Messenger protocols.
	Specifies the port or ports to open for this rule. If this list is specified, these ports will not be blocked.
	You can specify either a single port or an inclusive range of ports separated by a dash (-). For example, to open port 25, specify <b>25</b> . To open ports 5000 to 5020 inclusive, specify <b>5000-5020</b> . Multiple ports or port ranges must be separated by a comma (,) or semicolon (;). For example, <b>25</b> , <b>36</b> ; <b>8080</b> , <b>5000-5020</b> . You can also press ENTER after each entry.
	<b>Note:</b> If you specify ports and do not specify hosts, users can access all hosts available through the specified ports.
SSL	Applies to the FTP, HTTP, ICQ/AOL Messenger, IRC, Jabber, SMTP, and Web Mail protocols.
	<ul> <li>Sets the SSL options. The following SSL options are available:</li> <li>Allowed Allows SSL connections.</li> </ul>
	Denied Disallows SSL connections.
	Required Requires that all connections use SSL.
Local sender ID(s):	Applies to the ICQ/AOL Messenger, Jabber, Mail.ru Agent, Windows Messenger, and Yahoo Messenger protocols.
	Specifies a list of identifiers for local users who are allowed to send instant messages. If this list is specified, instant messages from these users will not be blocked.
	ICQ/AOL Messenger users are identified by numbers called UIN (for example, <b>111222, 23232323</b> ).
	Jabber users are identified by Jabber IDs in the following format: user@example.com.
	Mail.ru Agent users are identified by mail.ru e-mail addresses in the following format: <b>user@mail.ru</b> .
	Windows Messenger users are identified by e-mail addresses in the following format: <b>user@example.com</b> .

PARAMETER	DESCRIPTION
	<ul> <li>Yahoo Messenger users are identified by any of the following user ID types:</li> <li>Yahoo! ID (<username> or <username>@yahoo.com)</username></username></li> <li>Rocketmail (<username>@rocketmail.com)</username></li> <li>Ymail (<username>@ymail.com)</username></li> </ul>
	Multiple user identifiers must be separated by a comma (,) or semicolon (;). You can also press ENTER after each entry.
Remote recipient ID(s):	Applies to the ICQ/AOL Messenger, Jabber, Mail.ru Agent, and Yahoo Messenger protocols.
	Specifies a list of identifiers for remote users who are allowed to receive instant messages. If this list is specified, instant messages to these users will not be blocked.
	ICQ/AOL Messenger users are identified by numbers called UIN (for example, <b>111222, 23232323</b> ).
	Jabber users are identified by Jabber IDs in the following format: user@example.com.
	Mail.ru Agent users are identified by mail.ru e-mail addresses in the following format: <b>user@mail.ru</b> .
	Windows Messenger users are identified by e-mail addresses in the following format: <b>user@example.com</b> .
	Yahoo Messenger users are identified by any of the following user ID types:
	Yahoo! ID ( <username> or <username>@yahoo.com)</username></username>
	Rocketmail ( <username>@rocketmail.com)</username>
	• Ymaii ( <username>@ymaii.com)</username>
	Multiple user identifiers must be separated by a comma (,) or semicolon (;). You can also press ENTER after each entry.
Local sender	Applies to the SMTP and Web Mail protocols.
Email(s):	Specifies a list of allowed e-mail senders for this rule. If this list is specified, mail from these senders will not be blocked.
	Use the following format for a sender address: <i>user@domain.com</i> . You can use the asterisk (*) as a wildcard character to specify a group of recipients. You can add the asterisk before or after the at sign (@) in an e-mail address. For example, to allow mail delivery from all users in a domain, type <b>*@domain.com</b> .
	Multiple e-mail addresses must be separated by a comma (,) or semicolon (;). You can also press ENTER after each entry.
	<b>Note:</b> When adding senders/recipients to the white list for Web Mail, consider the following: Messages sent from a Webmail application are kept in the Sent Items folder and can be forwarded to any address from any computer.
Remote	Applies to the SMTP and Web Mail protocols.
recipient Email(s):	Specifies a list of allowed e-mail recipients for this rule. If this list is specified, mail to these recipients will not be blocked.
	Use the following format for a recipient address: <i>user@domain.com</i> . You can use the asterisk (*) as a wildcard character to specify a group of recipients. You can

PARAMETER	DESCRIPTION
	add the asterisk before or after the at sign (@) in an e-mail address. For example, to allow mail delivery to all users in a domain, type <b>*@domain.com</b> .
	Multiple e-mail addresses must be separated by a comma (,) or semicolon (;). You can also press ENTER after each entry.
Social Networks	Applies to the Social Networks protocol. Specifies a list of allowed social networking sites for this rule. If this list is specified, these social networking sites will not be blocked. The following social networking sites are supported: Facebook, Google+, LinkedIn, LiveJournal, MeinVZ, Myspace, Odnoklassniki, SchuelerVZ, StudiVZ, Tumblr, Twitter, Vkontakte, XING.
Web Mail Services	Applies to the Web Mail protocol. Specifies a list of allowed Web-based e-mail services for this rule. If this list is specified, e-mail messages sent through these mail services will not be blocked. The following Web-based e-mail services are supported: AOL Mail, Gmail, GMX Mail, Hotmail, Mail.ru, Rambler Mail, Web.de, Yahoo! Mail, and Yandex Mail.

**Note:** You can define different online vs. offline Protocols White Lists for the same user or sets of users. The online Protocols White List (Regular Profile) applies to client computers that are working online. The offline Protocols White List (Offline Profile) applies to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "DeviceLock Security Policies (Offline Profile)." For information about how to define the offline Protocols White List, see "Managing Offline Protocols White List."

Managing the online (regular) Protocols White List involves the following tasks:

- Defining the Protocols White List
- Editing the Protocols White List
- Copying rules of the Protocols White List
- Exporting and importing the Protocols White List
- Undefining the Protocols White List
- Deleting rules of the Protocols White List

## **Defining Protocols White List**

### To define the Protocols White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.

- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLoc**k.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click White List, and then click Manage.
    - OR -
  - Select **White List**, and then click **Manage** on the toolbar.

The Protocols White List dialog box appears.

Protocols White List		? 🔀
Users:	Rules:	
Users	Description Protocol Hosts	Ports SSL Extra parameters
Add Delete	Add Edit Delete	Load Save
		OK Cancel Apply

4. In the left pane of the **Protocols White List** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

5. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups for which you want to define the Protocols White List, and then click **OK**.

The users and groups that you added are displayed under Users in the left pane of the Protocols White List dialog box.

To delete a user or group, in the left pane of the **Protocols White List** dialog box, under **Users**, select the user or group, and then click **Delete**.

6. In the left pane of the **Protocols White List** dialog box, under **Users**, select the user or group.

*You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.* 

7. In the right pane of the **Protocols White List** dialog box, under **Rules**, click **Add**.

The Add Rule dialog box appears.

📑 Add Rule	? 🗙
Protocol:	
Description.	OK Cancel

- 8. In the **Add Rule** dialog box, specify general and protocol-specific parameters for this rule. To specify general parameters, do the following:
  - To specify the protocol, in the **Protocol:** list, click the protocol of your choice.
  - To specify the rule name, in the **Description** box, type a name.

To specify protocol-specific parameters, do the following:

- To specify the hosts, in the **Hosts:** box, type host names or IP addresses separated by a comma or semicolon. For more information on how to specify hosts, see the <u>description of the Hosts parameter</u> earlier in this section.
- To specify the ports, in the **Ports:** box, type port numbers separated by a comma or semicolon. For more information on how to specify ports, see the <u>description of the Ports parameter</u> earlier in this section.
- To configure the SSL options, under **SSL**, click any of the following: **Allowed** (allows SSL connections), **Denied** (disallows SSL connections), or **Required** (requires that all connections use SSL).
- To specify the IM local sender ID(s), in the Local sender ID(s): box, type user identifiers separated by a comma or semicolon. For more information on how to specify user identifiers, see the <u>description of the Local sender ID(s)</u> <u>parameter</u> earlier in this section.
- To specify the IM remote recipient ID(s), in the Remote recipient ID(s): box, type user identifiers separated by a comma or semicolon. For more information on how to specify user identifiers, see the <u>description of the</u> <u>Remote recipient ID(s) parameter</u> earlier in this section.
- To specify the e-mail senders, in the Local sender Email(s): box, type sender addresses separated by a comma or semicolon. For more information on how to specify sender addresses, see the <u>description of the Local sender</u> <u>Email(s): parameter</u> earlier in this section.
- To specify the e-mail recipients, in the **Remote recipient Email(s):** box, type recipient addresses separated by a comma or semicolon. For more information on how to specify recipient addresses, see the <u>description of the Remote recipient Email(s): parameter</u> earlier in this section.
- To specify the social networking sites, under **Social Networks**:, select the appropriate check boxes. For more information, see the <u>description of the</u> <u>Social Networks: parameter</u> earlier in this section.
- To specify the Web-based e-mail services, under **Web Mail Services**:, select the appropriate check boxes. For more information, see the <u>description of the</u> <u>Web Mail Services: parameter</u> earlier in this section.
- 9. Click **OK**.

*The rule you created is displayed under Rules in the right pane of the Protocols White List dialog box.* 

### 10. Click **OK** or **Apply**.

The users or groups to which the white list rule applies are displayed under White List in the console tree.

When you select a user or group to which a white list rule applies in the console tree, in the details pane you can view detailed information regarding this rule. This information includes the following:

- **Protocol** The protocol the rule applies to.
- **Description** The name of the rule.
- **Hosts** Shows the allowed hosts for this rule.
- **Ports** Shows the allowed ports for this rule.
- **SSL** Shows the selected SSL option. Possible values: **Allowed** (allows SSL connections), **Denied** (disallows SSL connections), and **Required** (requires that all connections use SSL).
- **Extra parameters** Shows additional protocol-specific parameters specified for the rule. These parameters include: **From** (shows allowed sender identifiers for instant messaging and e-mail sender addresses for Webmail) and **To** (shows allowed recipient identifiers for instant messaging and e-mail recipient addresses for Webmail).
- **Profile** Possible values: **Regular** and **Offline**. **Regular** indicates that the rule applies to client computers that are working online. **Offline** indicates that the rule applies to computers that are working offline.

You can define different online vs. offline Protocols White Lists for the same user or sets of users. For information about how to define the offline Protocols White List, see "<u>Managing Offline Protocols White List</u>."

## **Editing Protocols White List**

You can modify parameter values specified for a white list rule any time you want.

### To edit a white list rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLoc**k.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, right-click **White List**, click **Manage**, and then do the following:
  - a) In the left pane of the **Protocols White List** dialog box, under **Users**, select the user or group for which you want to edit the rule.

By selecting users or groups, you can view the white list rules applied to them under Rules in the right pane of the dialog box.

b) In the right pane of the Protocols White List dialog box, under Rules, select the rule you want to edit, and then click Edit.
 - OR -

Right-click the rule, and then click **Edit**.

- OR -

Under Protocols, expand White List, and then do the following:

a) Under **White List**, select the user or group for which you want to edit the rule.

By selecting users or groups, you can view the white list rules applied to them in the details pane.

b) In the details pane, right-click the rule you want to edit, and then click Edit.
 - OR -

In the details pane, double-click the rule you want to edit.

The Edit Rule dialog box appears.

- 4. In the **Edit Rule** dialog box, modify the rule parameters as required to meet your needs.
- 5. Click **OK** to apply the changes.

## **Copying Rules of Protocols White List**

You can perform a cut-and-paste operation, a copy-and-paste operation or a drag-and-drop operation to reuse existing rules of the Protocols White List.

#### To copy a white list rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLoc**k.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click White List, and then click Manage.
     OR -
  - Select White List, and then click Manage 📑 on the toolbar.

The Protocols White List dialog box appears.

4. In the left pane of the **Protocols White List** dialog box, under **Users**, select the user or group to which the rule that you want to copy is applied.

By selecting users or groups, you can view the white list rules applied to them under Rules in the right pane of the dialog box.

5. In the right pane of the **Protocols White List** dialog box, under **Rules**, right-click the rule you want to copy, and then click **Copy** or **Cut**.

The rule you cut or copy is automatically copied to the Clipboard.

You can use the CTRL+C, CTRL+X and CTRL+V key combinations to copy, cut and paste the rule. When you use the CTRL+X key combination to cut the rule, the rule will be cut only after you paste it.

6. In the left pane of the **Protocols White List** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

7. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups to which you want to apply the copied rule, and then click **OK**.

*The users and groups that you added are displayed under Users in the left pane of the Protocols White List dialog box.* 

8. In the left pane of the **Protocols White List** dialog box, under **Users**, select the users or groups to which you want to apply the copied rule.

You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

9. In the right pane of the **Protocols White List** dialog box, right-click in the **Rules** pane and then click **Paste**.

The copied rule is displayed under Rules in the right pane of the Protocols White List dialog box.

10. Click **OK** or **Apply** to apply the copied rule.

## **Exporting and Importing Protocols White List**

You can export all your current rules of the Protocols White List to a .pwl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

### To export the Protocols White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand DeviceLock.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
- 4. Under **Protocols**, do one of the following:
  - Right-click White List, and then click Save. - OR -
  - Select **White List**, and then click **Save I** on the toolbar. - OR -
  - Expand White List, right-click any user or group specified in the white list, and then click **Save**.
    - OR -
  - Expand White List, select any user or group specified in the white list. In the details pane, right-click the white list rule, and then click **Save**. - OR -
  - Expand White List, select any user or group specified in the white list, and • then click **Save** 🗟 on the toolbar. - OR -
  - Right-click **White List**, and then click **Manage**. In the right pane of the Protocols White List dialog box, under Rules, click Save.

The Save As dialog box appears.

- 5. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .pwl file.
- 6. In the **File name** box, type the file name you want.
- 7. Click Save.

When you export the Protocols White List, it is saved in a file with a .pwl extension.

### To import the Protocols White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand DeviceLock.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:

- Right-click White List, and then click Load.
   OR -
- Select White List, and then click Load on the toolbar.
   OR -
- Expand **White List**, right-click any user or group specified in the white list, and then click **Load**.
  - OR -
- Expand White List, select any user or group specified in the white list. In the details pane, right-click the white list rule, and then click Load.
   OR -
- Expand White List, select any user or group specified in the white list, and then click Load in the toolbar
- Right-click White List, and then click Manage. In the right pane of the **Protocols White List** dialog box, under **Rules**, click **Load**.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open**.

*If the Protocols White List is already defined and you choose to import a new white list, the following message box is displayed.* 

DeviceL	ock	×
2	Do you want to overwrite existing records (Yes - Overwrite, No - Appen	d)?
	Yes No Cancel	

In the message box, click **Yes** to overwrite the existing white list. Click **No** to append a new white list to the existing white list.

## **Undefining Protocols White List**

If you deploy DeviceLock policies using DeviceLock Group Policy Manager or DeviceLock Service Settings Editor, in some situations you may want to prevent the Protocols White List from being applied to a specific group of client computers. To do so, you need to return the previously defined white list to the unconfigured state. All undefined DeviceLock settings are ignored by client computers.

#### To undefine the Protocols White List

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, right-click DeviceLock Settings or DeviceLock Service, and then click Load Service Settings to open the XML file with defined DeviceLock policies

c) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand Protocols.
- 3. Under **Protocols**, right-click **White List**, and then click **Undefine**.

## **Deleting Rules of Protocols White List**

You can delete individual white list rules when they are no longer required.

#### To delete a white list rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLoc**k.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Expand **White List**, right-click the user or group to which the rule is applied, and then click **Delete user**.

When you delete a user or group, the rule associated with this user or group is automatically deleted.

- OR -

• Expand **White List**, and then select the user or group to which the rule is applied. In the details pane, right-click the rule associated with this user or group, and then click **Delete**.

- OR -

• Right-click White List, and then click Manage. In the left pane of the **Protocols White List** dialog box, under **Users**, select the user or group to which the rule is applied. In the right pane of the **Protocols White List** dialog box, under **Rules**, select the rule, and then click **Delete** or right-click the rule, and then click **Delete**.

## **Managing Security Settings for Protocols**

You can define additional security parameters that affect permissions and audit rules for protocols.

DeviceLock supports these additional security parameters:

- Block unrecognized outgoing SSL traffic if enabled, allows DeviceLock Service to audit and block all unrecognized outgoing SSL traffic. Otherwise, even if the protocols are locked, all unrecognized outgoing SSL traffic is not blocked and audit is not performed for it.
- Block IP addresses in URL if enabled, allows DeviceLock Service to block all URLs containing the host IP address when users have "allow access" permissions for a protocol. Use this setting to block access to sites (for example, Facebook) that can be accessed using an IP address. This setting applies to the following protocols: HTTP, Social Networks, and Web Mail. By default, the setting is disabled.

Audit and shadow copying for URLs containing the host IP address are performed at the HTTP level. If Block IP addresses in URL is disabled but users have "deny access" permissions for a protocol, all URLs containing the host IP address are also blocked.

**Note:** If **Block IP addresses in URL** is enabled and specific host IP addresses are allowed by the Protocols White List, these IP addresses will not be blocked. The Protocols White List settings override Security Settings for protocols.

**Note:** You can define different online vs. offline Security Settings for the same user or sets of users. Online Security Settings (Regular Profile) apply to client computers that are working online. Offline Security Settings (Offline Profile) apply to client computers that are working offline. By default, DeviceLock works in offline mode when the network cable is not connected to the client computer. For detailed information on DeviceLock offline policies, see "<u>DeviceLock Security Policies (Offline Profile</u>)." For information about how to define offline Security Settings, see "<u>Managing Offline Security Settings</u> for Protocols."

Managing online (regular) Security Settings for protocols involves the following tasks:

- Defining and changing Security Settings
- Undefining Security Settings

STATE	DESCRIPTION
Not Configured	Indicates that Security Settings are not defined for protocols.
Enabled	Indicates that Security Settings are enabled for protocols.
Disabled	Indicates that Security Settings are disabled for protocols.

Online Security Settings for protocols can have one of the following states:

## **Defining and Changing Security Settings**

## To define and change Security Settings

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Select **Security Settings**. In the details pane, right-click the Security Setting, and then click **Enable** or **Disable**.

When you select Security Settings in the console tree, they are displayed in the details pane.

- OR-

• Right-click **Security Settings**, and then click **Manage**. In the **Security Settings** dialog box that opens, select or clear the appropriate check box, and then click **OK**.

To open the Security Settings dialog box, you can also select Security Settings, and then click Manage B on the toolbar.

## **Undefining Security Settings**

If you deploy DeviceLock policies using DeviceLock Group Policy Manager or DeviceLock Service Settings Editor, in some situations you may want to prevent Security Settings defined for protocols from being applied to a specific group of client computers. To do so, you need to return the previously defined Security Settings to the unconfigured state. All undefined DeviceLock settings are ignored by client computers.

### **To undefine Security Settings**

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, right-click DeviceLock Settings or DeviceLock Service, and then click Load Service Settings to open the XML file with defined DeviceLock policies
  - c) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

a) Open Group Policy Object Editor.

- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, select **Security Settings**.

When you select Security Settings in the console tree, they are displayed in the details pane.

4. In the details pane, right-click the Security Setting you want to undefine, and then click **Undefine**.

# **DeviceLock Reports**

DeviceLock lets you create reports using data from logs stored on DeviceLock Enterprise Server. Use reports to arrange and display statistical data on a user's device- and protocolrelated activities in a separate file. When generating a report, you can define report parameters to filter the data and display the information that is relevant to you. For example, you can specify the start and end date and time of the report period for which data is displayed.

Reports can be created, automatically sent to you via e-mail, stored, exported to a variety of formats and shared with others. Reports are created by using DeviceLock Management Console.

## **Report Categories and Types**

DeviceLock comes with a set of predefined report templates that you can use to create new reports. These predefined templates are displayed in the console tree, under **DeviceLock Enterprise Server**, **Reports**.



**Note:** You can create only those reports that are based on the predefined templates. You cannot modify the predefined report templates or create your own (custom) report templates.

There are two categories of report templates:

- Audit Log reports
- Shadow Log reports

The report types available in each category are described below.

**Note:** When you upgrade to DeviceLock version 7.0, the previously generated reports are automatically updated with the new name. The name of the Allowed & Denied access requests per device type reports changes to Allowed & Denied access requests per channel. The name of the Allowed vs. Denied device access reports changes to Allowed vs. Denied access requests. The name of the Copied files per device type reports changes to Copied files per channel.

## Audit Log Reports

Audit Log reports are reports that use the DeviceLock Enterprise Server audit log files as a data source. The following table provides summary information on the report types available in this category.

REPORT TYPE	DESCRIPTION
Allowed & Denied access requests per	This report shows the number of allowed and denied access requests per data transmission channel (devices and/or protocols).
	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
channel	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	<ul> <li>User(s): Shows the users that were specified for the report.</li> </ul>
	<ul> <li>Channel(s): Shows the data transmission channels that were specified for the report. The available options are: all devices, all protocols, and all devices and protocols.</li> </ul>
	The Report Results section contains a table and a chart that show detailed results of the report. The table has the following columns:
	Channel Shows a data transmission channel.
	<ul> <li>Allowed Shows the number of allowed access requests.</li> <li>Denied Shows the number of denied access requests.</li> </ul>
	• Demed Shows the humber of demed access requests.
Allowed vs. Denied	This report shows the total number of allowed and denied access requests sent through all data transmission channels (devices and/or protocols).
access requests	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>

REPORT TYPE	DESCRIPTION
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	<ul> <li>User(s): Shows the users that were specified for the report.</li> </ul>
	<ul> <li>Channel(s): Shows the data transmission channels that were specified for the report. The available options are: all devices, all protocols, and all devices and protocols.</li> </ul>
	The Report Results section contains a table and a pie chart that show detailed results of the report. The table has the following rows:
	<ul> <li>Allowed Shows the total number of allowed access requests and the respective percentage.</li> </ul>
	<ul> <li>Denied Shows the total number of denied access requests and the respective percentage.</li> </ul>
	<ul> <li>Total Shows the total number of all access requests and the respective percentage.</li> </ul>
	The pie chart represents the report results in percentages.
Read & Write access	This report shows the number of read and write access requests per device type. The report provides data only for the Floppy, iPhone, Removable, Hard disk, DVD/CD-ROM, Tape, Windows Mobile, and Palm device types.
requests per device type	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
<i>,</i> ,	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• Access Type(s): Shows the event types that were specified for the report.
	<ul> <li>Computer(s): Shows the computers that were specified for the report.</li> </ul>
	<ul> <li>User(s): Shows the users that were specified for the report.</li> </ul>
	The Report Results section contains a table and a chart that show detailed results of the report. The table has the following columns:
	Device Type Shows a device type.
	Read Shows the number of read access requests.
	Write Shows the number of write access requests.
	The table also has a <b>Total</b> row that sums up all the values in the <b>Read</b> and <b>Write</b> columns.
Top active computers	This report shows the most frequently used computers sorted according to the number of allowed and denied access requests. By default, the report lists the first 10 computers but you can specify any number of computers.
	The report consists of three sections: the Report Header, Report Parameters, and

REPORT TYPE	DESCRIPTION
	Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	<ul> <li>Channel(s): Shows the device types and/or protocols that were specified for the report.</li> </ul>
	The Report Results section contains two tables with detailed results of the report. Table 1 lists the top N (where N is a specific number) computers having allowed access. Table 2 lists the top N (where N is a specific number) computers having denied access. These tables have the following columns:
	Computer Name Shows a computer name
	Access Count Shows the number of access requests. Values in this column are sorted in descending order.
Top active users	This report shows the most active users sorted according to the number of allowed and denied access requests sent by each user. By default, the report lists the first 10 users but you can specify any number of users.
	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	<ul> <li>Channel(s): Shows the device types and/or protocols that were specified for the report.</li> </ul>
	The Report Results section contains two tables with detailed results of the report. Table 1 lists the top N (where N is a specific number) users having allowed access. Table 2 lists the top N (where N is a specific number) users having denied access. These tables have the following columns:
	User Name Shows a user name
	Access Count Shows the number of access requests. Values in this column are sorted in descending order.

REPORT TYPE	DESCRIPTION
Top inserted USB & FireWire devices	This report shows the most frequently inserted USB and FireWire devices sorted according to the number of the Insert actions. By default, the report lists the first 10 devices but you can specify any number of devices.
	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	• <b>Users(s):</b> Shows the users that were specified for the report.
	The Report Results section contains a table with detailed results of the report. This table has the following columns:
	Device Name Shows a device name
	• <b>Insert Count</b> Shows the number of the Insert actions. Values in this column are sorted in descending order.
Top used USB devices	This report shows the most frequently used USB devices sorted according to the number of the allowed and denied access requests. By default, the report lists the first 10 devices but you can specify any number of devices.
	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	• <b>Users(s):</b> Shows the users that were specified for the report.
	The Report Results section contains two tables with detailed results of the report. Table 1 lists the top N (where N is a specific number) USB devices having allowed access. Table 2 lists the top N (where N is a specific number) USB devices having denied access. These tables have the following columns:
	Device Name Shows a device name
	<ul> <li>Access Count Shows the number of access requests. Values in this column are sorted in descending order.</li> </ul>

## Shadow Log Reports

Shadow Log reports are reports that use the DeviceLock Enterprise Server shadow log files as a data source. All reports contain the combined data from the shadow log and deleted shadow log. The following table provides summary information on the report types available in this category.

REPORT TYPE	DESCRIPTION
Copied files per channel	This report shows statistics on copied files per data transmission channel (devices and/or protocols). Statistical information on copied files is sorted according to the number of copied files and total size of all copied files.
	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	• <b>Users(s):</b> Shows the users that were specified for the report.
	• <b>File Name:</b> Shows the files that were specified for the report.
	<ul> <li>Channel(s): Shows the data transmission channels that were specified for the report. The available options are: all devices, all protocols, and all devices and protocols.</li> </ul>
	The Report Results section contains two tables and two pie charts that show detailed results of the report. Table 1 shows the number of copied files for each data transmission channel. Table 1 has the following columns:
	Channel Shows a data transmission channel.
	Number of Files Shows the number of copied files.
	Table 1 also has a <b>Total</b> row that sums up all the values in the <b>Number of Files</b> column.
	Table 2 shows the total size of copied files for each data transmission channel. Table 2 has the following columns:
	Channel Shows a data transmission channel.
	Data Size Shows the total size of all copied files.
	Table 2 also has a <b>Total</b> row that sums up all the values in the <b>Data Size</b> column.
	Each table is followed by a pie chart which represents the report results in percentages.
Top active computers	This report shows the most frequently used computers sorted according to the number of copied files and total size of all copied files. By default, the report lists the first 10 computers but you can specify any number of computers.
	The report consists of three sections: the Report Header, Report Parameters, and

REPORT TYPE	DESCRIPTION
	Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	<ul> <li>Channel(s): Shows the device types and/or protocols that were specified for the report.</li> </ul>
	• <b>File Name:</b> Shows the files that were specified for the report.
	The Report Results section contains two tables with detailed results of the report. Table 1 lists the top N (where N is a specific number) computers by the number of copied files. Table 1 has the following columns:
	Computer Name Shows a computer name
	• <b>Number of Files</b> Shows the number of copied files. Values in this column are sorted in descending order.
	Table 2 lists the top N (where N is a specific number) computers by the amount of copied data. Table 2 has the following columns:
	Computer Name Shows a computer name
	Data Size Shows the total size of all copied files. Values in this column are sorted in descending order.
Top active users	This report shows the most active users sorted according to the number of copied files and total size of all copied files. By default, the report lists the first 10 users but you can specify any number of users.
	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	<ul> <li>Channel(s): Shows the device types and/or protocols that were specified for the report.</li> </ul>
	• <b>File Name:</b> Shows the files that were specified for the report.
	The Report Results section contains two tables with detailed results of the report. Table 1 lists the top N (where N is a specific number) users by the number of copied files. Table 1 has the following columns:

REPORT TYPE	DESCRIPTION
	User Name Shows a user name
	<ul> <li>Number of Files Shows the number of copied files. Values in this column are sorted in descending order.</li> </ul>
	<ul> <li>Table 2 lists the top N (where N is a specific number) users by the amount of copied data. Table 2 has the following columns:</li> <li>User Name Shows a user name</li> </ul>
	• <b>Data Size</b> Shows the total size of all copied files. Values in this column are sorted in descending order.
Top copied files	This report shows the most frequently copied files sorted according to the number of copied files and total size of all copied files. By default, the report lists the first 10 files but you can specify any number of files.
	The report consists of three sections: the Report Header, Report Parameters, and Report Results.
	The Report Header section contains the report title that appears at the very beginning of the report. The report title shows the report type.
	The Report Parameters section contains information on the report parameters you specify when generating the report. This information includes:
	<ul> <li>Period from: to: Shows the start and end date and time of the report period for which data is displayed.</li> </ul>
	The date/time format for the Period from: and to: fields is determined by the date/time format for the user account under which DeviceLock Enterprise Server is running.
	• <b>Computer(s):</b> Shows the computers that were specified for the report.
	• <b>Channel(s):</b> Shows the device types and/or protocols that were specified for the report.
	• <b>Users(s):</b> Shows the users that were specified for the report.
	The Report Results section contains two tables with detailed results of the report. Table 1 lists the top N (where N is a specific number) copied files by quantity. Table 1 has the following columns:
	File Name Shows a file name
	<ul> <li>Number of Files Shows the number of copied files. Values in this column are sorted in descending order.</li> </ul>
	Table 2 lists the top N (where N is a specific number) copied files by size. Table 2 has the following columns:
	File Name Shows a file name
	• <b>Data Size</b> Shows the total size of all copied files. Values in this column are sorted in descending order.

## **Configuring E-mail Delivery of Reports**

DeviceLock allows you to distribute reports through e-mail. E-mail delivery of reports requires a Simple Mail Transport Protocol (SMTP) server. Before you can use e-mail delivery of reports, you must specify which SMTP server will be used to send the e-mail messages and which e-mail address will be used as the sender address.

#### To configure e-mail delivery of reports

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under **DeviceLock Enterprise Server**, right-click **Reports**, and then click **Notification Settings**.

- OR -

Select **Reports**, and then click **Notification Settings** 選 on the toolbar.

The Mail Server Parameter dialog box appears.

ail Server Parameters		?
Use e-mail noti	fications for reports	
SMTP host:		
Port:	25	<u> </u>
Server requi	res authentication —	
User name:		
Pass <u>w</u> ord:		
Sender Address		
		OK Cancel

4. In the **Mail Server Parameter** dialog box, do the following:

USE THIS	TO DO THIS
Use e-mail	Configure an e-mail notification for completed reports.
notifications for reports	Select the <b>Use e-mail notifications for reports</b> check box to type your e-mail information in the corresponding boxes.
	Clear the <b>Use e-mail notifications for reports</b> check box to remove the previously configured SMTP server and e-mail notification settings.
SMTP host	Specify the name of the SMTP server to use when sending messages.
	You can specify the SMTP server through an IP address or a DNS resolvable name.
Port	Specify the port that SMTP clients use to connect to the SMTP server. The default value is 25.
Server requires	Specify the type of authentication to use with the SMTP server.
authentication	Select the <b>Server requires authentication</b> check box to specify basic authentication.
	Clear the Server requires authentication check box to specify

USE THIS	TO DO THIS
	no authentication.
User name	Specify the user name to use for authentication with the SMTP server.
	This property requires a value if you specified basic authentication.
Password	Specify the password to use for authentication with the SMTP server.
	This property requires a value if you specified basic authentication.
Sender Address	Specify the e-mail address that will be used in the <b>From:</b> line of an e-mail message.

5. Click **OK**.

## **Setting Default Format for Reports**

You can specify the report output format you want to use for reports. The available options are:

- HTML Format (\*.htm)
- PDF Format (\*.pdf)
- Rich Text Format (\*.rtf)

DeviceLock uses PDF as the default output format for reports.

### To set the default format for reports

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under **DeviceLock Enterprise Server**, right-click **Reports**. Next point to **Set Default Format**, and then click any of the following options: **HTML**, **PDF**, **RTF**.

## **Defining Report Parameters**

Report parameters help you specify which data from the DeviceLock log files you want to use in a report. For example, you can specify a date range to restrict the data that appears in the report. Report parameters must be set for each report individually.

To define report parameters, use the **Report Options** dialog box. This dialog box appears in one of the following situations:

• When you right-click any report template in the console tree, and then click **New Report**.

• When you select any report template in the console tree, and then click **New report** on the toolbar.

## **Report Options Dialog Box**

#### Period from:.....To:

Specifies the start and end date and time of the report period for which data is displayed. The date format is MM/DD/YYYY where MM specifies the month, DD the day, YYYY the year. The time format is hh:mm:ss {AP}M, where hh the hour, mm the minute, ss the second, and {AP}M the AM or PM designation.

In the **Period from:** and **To:** boxes, type or select the date and time of the report period.

The default start and end time of the report period is the time at which the **Report Options** dialog box opens. The default end date of the report period is the current date. The default start date of the report period is the same day in an earlier month. For example, if the current date is March 5, 2009, the default end date of the report period is 3/5/2009 while the default start date is 2/5/2009.

### Computer(s):

Specifies computers for the report. The **Computer(s)** box is not displayed in the **Report Options** dialog box for the Top active computers report types.

The **Computer(s)** box is empty by default. This means that the report will display data for all computers in the DeviceLock Enterprise Server database.

To specify computers for the report, you can do any of the following:

In the Computer(s) box, type computer names using wildcards, such as asterisks
 (\*) and question marks (?). For example, if you specify \*.mydomain.com, the
 report will display data for all computers in mydomain.com.

An asterisk (\*) replaces an unlimited number of characters. The question mark (?) replaces a single character. You can use these wildcards in any position and in any quantity.

Multiple computer names must be separated by a comma (,) or semicolon (;).

- OR -

- Click **Browse** next to the **Computer(s):** box, and then do the following:
  - a) When the **Edit computers list** dialog box opens to the **Select computer(s)** list, click one of the following options:

OPTION	DESCRIPTION							
From Database	This option is selected by default. This option lets you select computers from the DeviceLock Enterprise Server database that shows all computers from which the server has ever received audit and							

OPTION	DESCRIPTION					
	shadow data. If you select this option:					
	<ol> <li>In the left pane of the dialog box, select the appropriate check boxes next to desired computers.</li> </ol>					
	2. Click the right single-arrow button 🗾.					
	The selected computers are displayed under Selected computers in the right pane of the dialog box.					
	To remove single computers from the list of selected computers, use the left single-arrow button <					
	To add or remove all available computers to or from the list of selected computers at the same time, use the right double-arrow button is or left double-arrow button is.					
From File	This option lets you select computers from an external text file. A text file must contain each computer's name or IP address on a separate line and can be either Unicode or non-Unicode. If you select this option:					
	<ol> <li>Click the ellipsis button location to open the <b>Open</b> dialog box and browse for the file to use.</li> </ol>					
	<ol><li>In the <b>Open</b> dialog box, in the <b>Look in</b> list, click the location that contains the file you want to import.</li></ol>					
	3. In the folder list, locate and open the folder that contains the file.					
	4. Click the file, and then click <b>Open</b> .					
	The computers from the file are displayed in the left pane of the Edit computers list dialog box.					
	<ol> <li>In the left pane of the Edit computers dialog box, select the desired computers, and then click the right single-arrow button</li> <li>.</li> </ol>					
	The selected computers are displayed under Selected computers in the right pane of the dialog box.					
	To remove single computers from the list of selected computers, use the left single-arrow button					
	To add or remove all available computers to or from the list of selected computers at the same time, use the right double-arrow button is or left double-arrow button is.					
Manual	This option lets you manually add computers that you want to select for the report. If you select this option:					
	1. In the left pane of the <b>Edit computers list</b> dialog box, type either computer names or IP addresses. Press the ENTER key after each computer name to make sure that each computer name is on a separate line.					
	<ol> <li>In the left pane of the <b>Edit computers</b> dialog box, select the desired computers, and then click the right single-arrow button</li> <li>.</li> </ol>					
	The selected computers are displayed under Selected computers in the right pane of the dialog box.					
	To remove single computers from the list of selected					
	To add or remove all available computers to or from the list of selected computers at the same time, use the right double- arrow button is or left double-arrow button selected.					

b) Click **OK**.

## Users

Specifies users for the report. The **User(s)** box is not displayed in the **Report Options** dialog box for the Top active computers and Top active users report types.

The **User(s)** box is empty by default. This means that the report will display data for all users in the DeviceLock Enterprise Server database.

To specify users for the report, do one of the following:

• In the **User(s) box**, specify user names using wildcards, such as asterisks (\*) and question marks (?). For example, if you specify **mydomain**\*, the report will display data for all users in mydomain.com.

An asterisk (\*) replaces an unlimited number of characters. The question mark (?) replaces a single character. You can use these wildcards in any position and in any quantity.

Multiple user names must be separated by a comma (,) or semicolon (;).

**Note:** You cannot specify user groups for the report.

- OR -

- Click Browse next to the User(s) box, and then do the following:
  - a) In the **Select Users** dialog box that opens, in the **Enter the object names to select** box, type the user account names that you want to specify for the report.

Multiple user names must be separated by a semicolon (;).

b) Click **OK**.

## Threshold

Specifies the time interval, in seconds, between logged events. This interval is used for event consolidation. It appears for all report types in the Audit Log report category except the Top inserted USB & FireWire devices report type.

Because a single user action often triggers multiple events, DeviceLock uses event consolidation when collecting events from the audit log for reporting purposes. DeviceLock compares the time element of an event with the time of subsequent events. When this time delta is less than or equal to the **Threshold** value, multiple events of the same type (either Allowed or Denied) are combined into a single summary event if all of the following conditions are true:

- The events are associated with the same computer
- The events are associated with the same device type

#### **Report Devices**

Select this option if you want to display data for all device types. If you do not select this option, information on all device-related activities will be excluded from the report. Appears only for Allowed & Denied access requests per channel, Allowed vs. Denied access requests, and Copied files per channel report types.

#### **Report Protocols**

Select this option if you want to display data for all protocols. If you do not select this option, information on all protocol-related activities will be excluded from the report. Appears only for Allowed & Denied access requests per channel, Allowed vs. Denied access requests, and Copied files per channel report types.

#### Send report via email

Select this option if you want to automatically send the generated report to individual users through e-mail. If you select this option, in the **Recipients** box, type the e-mail addresses of the recipients separated by commas, semicolons, or spaces. Use the following format: *user@mailserver* 

### Access type(s)

Specifies the types of events that you want to include in or exclude from the report. Appears only for the Read & Write access requests per device type report type in the Audit Log report category.

If you select the **Allowed** check box, the Success Audit events (that is, events that record successful access attempts) will be retrieved for the report. If you select the **Denied** check box, the Failure Audit events (that is, events that record failed access attempts) will be retrieved for the report. You can use either or both of these options to specify the types of events.

### Device type(s)

Specifies the device types for the report. Appears only for the Top active computers, Top active users, and Top copied files report types.

If you select this option, select the appropriate check boxes next to the device types you want to specify for the report.

### Protocol(s)

Specifies the protocols for the report. Appears only for the Top active computers, Top active users, and Top copied files report types.

If you select this option, select the appropriate check boxes next to the protocols you want to specify for the report.

**Note:** If you leave both options - **Device type(s)** and **Protocol(s)** unselected, the report will display data for all device types and protocols. If you select either of these options and then specify device type(s) or protocols, the report will display data only for the specified device type(s) or protocols.

#### **Top computers**

Specifies the number of the most frequently used computers. Appears only for the Top active computers report type.

The default value is 10. To change the default value, type or select the appropriate number of computers in the **Top computers** box.

#### **Top users**

Specifies the number of the most active users. Appears only for the Top active users report type.

The default value is 10. To change the default value, type or select the appropriate number of users in the **Top users** box.

#### **Top USB and FireWire devices**

Specifies the number of the most frequently inserted USB and FireWire devices. Appears only for the Top inserted USB & FireWire devices report type.

The default value is 10. To change the default value, type or select the appropriate number of devices in the **Top USB and FireWire devices** box.

#### **Top USB devices**

Specifies the number of the most frequently used USB devices. Appears only for the Top used USB devices report type.

The default value is 10. To change the default value, type or select the appropriate number of devices in the **Top USB devices** box.

#### File name

Specifies files for the report. Appears only for the Top active users, Top active computers, and Copied files per channel report types in the Shadow Log report category.

The **File name** box is empty by default. This means that the report will display data for all files in the DeviceLock Enterprise Server database.

To specify files for the report, in the **File name** box, type file names using wildcards, such as asterisks (\*) and question marks (?). For example, type **\*.txt** to specify all files that have the .txt extension. To continue the example, if you want to specify all files whose

names begin with any characters that contain the string "price" and have any extension, type **\*price\*.\*** 

An asterisk (\*) replaces an unlimited number of characters. The question mark (?) replaces a single character. You can use these wildcards in any position and in any quantity.

Multiple file names must be separated by a comma (,) or semicolon (;).

## **Managing Reports**

Managing DeviceLock reports involves the following tasks:

- Running reports
- Refreshing reports
- Viewing reports
- Viewing report parameters
- Exporting and saving reports
- Sending reports through e-mail
- Deleting reports

## **Running Reports**

#### To run a report

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under DeviceLock Enterprise Server, expand Reports.
- 4. Expand Audit Log or Shadow Log.
- 5. Under **Audit Log** or **Shadow Log**, right-click any report template you want to use, and then click **New report**.

The Report Options dialog box appears.

6. In the **Report Options** dialog box, accept or change the default settings, and then click **OK**.

*For information on the default settings and changing the default settings in the Report Options dialog box, see* "*Defining Report Parameters*."

While the report is being processed on DeviceLock Enterprise Server, the report execution information is displayed in DeviceLock Management Console. To view and analyze this information, in the console tree select the report template that you used for running a new report.

When you select a report template in the console tree, in the details pane you can view report execution information regarding all reports based on the selected template. Report execution information includes the following:

• **User** The name of the user who ran the report.

- From Computer The name of the computer used to run the report.
- **Started** The date and time when the report began to run.
- **Finished** The date and time when the report was finished.
- **E-mailed** Possible values: **Yes** and **No**. **Yes** indicates that the report included in the e-mail delivery was successfully delivered to some or all of the intended recipients. **Yes** is displayed only after the sending process is complete. **No** indicates one of the following:

The report is not included in the e-mail delivery.

- OR -

The report included in the e-mail delivery did not reach all of the intended recipients.

If an error occurs during the e-mail delivery of a report, you can use Server Log Viewer to determine the reason. For more information on Server Log Viewer, see "<u>Server Log Viewer</u>."

If your computer has anti-virus or anti-spam software installed and running and an error occurs during the e-mail delivery of a report, the error information may not be reported in the DeviceLock Enterprise Server log. This behavior occurs because anti-virus and anti-spam products, for example, Symantec Norton AntiVirus, can automatically intercept e-mail traffic.

For information about how your anti-virus or anti-spam program works, consult the manufacturer's documentation included with your program.

 Status Possible values: Generating, Ready, Error. Generating indicates that the report is being generated. Ready indicates that the report was successfully completed. Error indicates that an error occurred while the report was being generated.

If an error occurs while the report is being generated, you can do the following to determine the reason:

Click the error report to display the error message.

- OR -

Use Server Log Viewer. For more information on Server Log Viewer, see "Server Log Viewer."

## **Refreshing Reports**

Because current reports and the current status of reports are not updated automatically, you need to perform a refresh operation.

#### To refresh reports

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under **DeviceLock Enterprise Server**, expand **Reports**.
- 4. Expand Audit Log or Shadow Log.
- 5. Under **Audit Log** or **Shadow Log**, right-click any report template, and then click **Refresh**.

- OR -

Under **Audit Log** or **Shadow Log**, select the report template that you used for generating reports, and then do one of the following:

- Click Refresh on the toolbar.
   OR -
- In the details pane, right-click any report, and then click **Refresh**.

When you select a report template in the console tree, you can view the reports associated with it in the details pane.

## **Viewing Reports**

After a report is successfully completed, you can open it in DeviceLock Management Console.

#### To view a report

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under DeviceLock Enterprise Server, expand Reports.
- 4. Expand Audit Log or Shadow Log.
- 5. Under **Audit Log** or **Shadow Log**, select the report template that you used for generating the report you want to view.

When you select a report template in the console tree, you can view the reports associated with it in the details pane.

6. In the details pane, right-click the report you want to view, and then click **Open**.

The report opens in the application associated with the report default format you chose. By default, the report opens in the Adobe Acrobat Reader, because DeviceLock uses PDF as the default output format for reports.

If you want to open a report in PDF format, you must have Adobe Acrobat Reader installed on your computer. You can download Acrobat Reader from the Adobe Web site: <u>http://get.adobe.com/reader/</u>.

### **Viewing Report Parameters**

After you run a report, you can get information on the report parameters that you specified when generating the report.

#### To view report parameters

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under DeviceLock Enterprise Server, expand Reports.
- 4. Expand Audit Log or Shadow Log.

5. Under **Audit Log** or **Shadow Log**, select the report template that you used for generating the report.

When you select a report template in the console tree, you can view the reports associated with it in the details pane.

6. In the details pane, right-click the report, and then click **View parameters**.

The Report Options dialog box appears. In this dialog box, you can view the parameter values that you specified when generating the report.

## **Exporting and Saving Reports**

DeviceLock provides the ability to export generated reports to another format (such as HTML, PDF or RTF) and save them as files locally or on your network.

**Note:** When you save a report as HTML, it is saved as an .htm file. If this report contains graphic images, each image is saved as a .gif file in the same directory as the .htm file.

#### To export and save reports

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under DeviceLock Enterprise Server, expand Reports.
- 4. Expand Audit Log or Shadow Log.
- 5. Under **Audit Log** or **Shadow Log**, select the report template that you used for generating the report you want to export and save.

When you select a report template in the console tree, you can view the reports associated with it in the details pane.

- 6. If you want to export and save a single report, do the following:
  - a) In the details pane, right-click the report you want to export and save, point to Save As, and then click any of the following options: HTML, PDF, RTF. The Save As dialog box appears.
  - b) In the **Save As** dialog box, in the **Save** in box, browse to the location where you want to save the report.
  - c) In the File name box, type the file name you want. By default, the file name is {Report\_Type}- [{dd.mm.yy hh:mm:ss}] where {dd.mm.yy hh:mm:ss} is the current date and time.
  - d) Click Save.

If you save a report as HTML and the report contains one or more graphic images, the images will be extracted from the report and saved as separate .gif files along with the .htm file in the same directory.

If you want to export and save multiple reports, do the following:

a) In the details pane, select multiple reports by holding down the SHIFT key or the CTRL key while clicking them.

b) Right-click the selection, point to Save As, and then click any of the following options: HTML, PDF, RTF.
 The Pressure for folder disland have an appear.

The Browse for folder dialog box appears.

c) In the **Browse for folder** dialog box, select the folder in which you want to save the reports, and then click **OK**.

## Sending Reports Through E-mail

DeviceLock provides the ability to send generated reports through e-mail.

#### To send generated reports through e-mail

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under DeviceLock Enterprise Server, expand Reports.
- 4. Expand Audit Log or Shadow Log.
- 5. Under **Audit Log** or **Shadow Log**, select the report template that you used for generating the report you want to send through e-mail.

When you select a report template in the console tree, you can view the reports associated with it in the details pane.

6. In the details pane, right-click the report you want to send, and then click **Send via e-mail**.

You can select multiple reports by holding down the SHIFT key or the CTRL key while clicking them.

The Send report via e-mail dialog box appears.

- In the Send report via e-mail dialog box, in the Recipients box, type the e-mail addresses of the recipients separated by commas, semicolons, or spaces. Use the following format: user@mailserver.
- 8. Click **OK**.

If an error occurs during the e-mail delivery of a report, an appropriate error message will be logged. You can use Server Log Viewer to determine the reason. For more information on Server Log Viewer, see "<u>Server Log Viewer</u>."

**Note:** When you send a report in HTML format, the report is included in the body of the e-mail message and is not sent as an attachment.

## **Deleting reports**

You can delete reports when they are no longer required.

#### To delete reports

- 1. Open DeviceLock Management Console and connect it to the computer running DeviceLock Enterprise Server.
- 2. In the console tree, expand **DeviceLock Enterprise Server**.
- 3. Under **DeviceLock Enterprise Server**, expand **Reports**.

- 4. Expand Audit Log or Shadow Log.
- 5. Under **Audit Log** or **Shadow Log**, select the report template that you used for generating the report you want to delete.

By selecting a report template in the console tree, you can view the reports associated with it in the details pane.

6. In the details pane, right-click the report you want to delete, and then click **Delete**.

You can delete multiple reports at the same time. To do this, do the following:

- a) In the details pane, select multiple reports by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Delete**.

# **DeviceLock Security Policies (Offline Profile)**

Today, organizations have many users who must continue working with business-critical information when they are disconnected from the corporate network. For example, traveling sales representatives, insurance agents and regional inspectors increasingly use corporate laptops or notebooks at disconnected locations. Protecting the sensitive information on these mobile computers has become a priority for many organizations.

DeviceLock provides greater protection of sensitive corporate information in disconnected environments. Now you can control user access to devices and protocols as well as shadow copying of the data written by the user or transmitted over the network in different offline scenarios. DeviceLock also offers more management flexibility, as you can define different online vs. offline security policies for the same user or set of users.

A user's online policies are applied when connected to the corporate network, or specified DeviceLock Enterprise Servers, or Active Directory domain controllers. Offline policies are applied when the user is working disconnected from the corporate network, or specified DeviceLock Enterprise Servers, or Active Directory domain controllers.

To configure DeviceLock to enforce different policies for online vs. offline scenarios begin by setting permissions for two profile types:

- **Regular Profile**. These settings are used by client computers that are working online.
- **Offline Profile**. These settings are used by client computers that are working offline, for example, when corporate users travel with laptop computers. If offline profile settings are not configured, regular profile settings are used instead.

You can use different regular vs. offline profiles for Permissions, Auditing and Shadowing, USB Devices White List, Media White List, Protocols White List, Content-Aware Rules, and Security Settings. You can manage offline profile settings using DeviceLock Management Console, DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.

The following examples describe typical scenarios in which you are likely to set different online vs. offline security policies to better protect your corporate data.

Scenario 1. Suppose you have a Finance group in your organization. As an administrator, you can allow members of this group to write files to Removable, DVD/CD-ROM, USB, and Floppy devices when they work online. Their online activity will be audited. Any copied files will be shadow copied; and audit and shadow logs will be sent to DeviceLock Enterprise Server. When offline, members of the Finance group will be denied write access.

These security policies let you monitor the activity of the Finance group members in real-time mode. By examining audit and shadow logs on DeviceLock Enterprise Server (often on a daily basis), you can respond promptly and appropriately when a data leakage incident occurs. In this case, a user will not be able to copy sensitive information to a device while offline in an attempt to avoid sending shadow copies to *DeviceLock Enterprise Server and thus alerting the Security department of the data theft.* 

• Scenario 2. Imagine Mary, a sales representative of a large company, who has a notebook computer and frequently works out of the office. She needs to be able to provide her business partners with information files resulting from her work. In this situation, you can allow Mary to write certain files to Removable, DVD/CD-ROM, USB, and Floppy devices and enable shadow copying of these files when she works offline. When online, she will be denied write access to the specified device types.

These security policies give you greater flexibility in managing users within an organization while providing better corporate data security.

## **Configuring Offline Mode Detection Settings**

You can define the network characteristics that DeviceLock uses to detect its connection state (whether it is online or offline). By default, DeviceLock works in offline mode when the network cable is not connected to the client computer.

## To configure offline mode detection settings

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Select Service Options.

When you select Service Options in the console tree, they are displayed in the details pane.

- 3. In the details pane, do one of the following:
  - Right-click Offline mode detection, and then click Properties.
     OR -
  - Double-click Offline mode detection.

The Offline Mode Detection dialog box appears.



4. In the **Offline Mode Detection** dialog box, click any of the following options:

OPTION	DESCRIPTION						
Server connectivity	Indicates that the connection state of a client computer is determined by whether or not it can connect to the specified DeviceLock Enterprise Server.						
	Thus, a client computer works in online mode, if it can connect to any of the specified DeviceLock Enterprise Servers and send them audit and shadow logs. A client computer works in offline mode if it cannot authenticate with any of the specified DeviceLock Enterprise Servers or all of the specified DeviceLock Enterprise Servers become unavailable at the same time.						
<b>Best Practice:</b> The most reliable way to secure client/server communication is to use DeviceLock Certificate authentication. For client/server certificate authentication, the public key must be installed on Device Client computers, while the private key must be installed on Device Enterprise Server(s).							
	If the certificate (the private key) is installed only on DeviceLock Enterprise Server, the server will reject connections and client computers will work in offline mode. If the certificate (the public key) is installed only on client computers, the server and the client will authenticate each other once a connection is established though this type of authentication is less secure than certificate-based authentication. For detailed information on DeviceLock Certificates, see "DeviceLock Certificates."						
Domain	Indicates that the connection state of a client computer is determined by						
connectivity	whether or not it can connect to the appropriate Active Directory domain controller (a domain controller of the domain to which the client computer belongs).						
	Thus, a client computer works in online mode, if it can connect to the appropriate domain controller. A client computer works in offline mode, if the appropriate domain controller becomes unavailable.						
	A client computer that is not joined to a domain (a workgroup or stand- alone computer) always works in offline mode.						

OPTION	DESCRIPTION
Wired connectivity	Indicates that the connection state of a client computer is determined by whether or not the network cable is connected to the Network Interface Card (NIC). This is the simplest and least secure method of detecting the connection state.
	Thus, a client computer works in online mode, if the network cable is connected to the NIC. A client computer works in offline mode, if the network cable is disconnected from the NIC. Please note that wireless network connections (Wi-Fi, etc.) and modem connections are ignored. This option is selected by default.

5. Click **OK**.

## **Switching Between Online and Offline Mode**

DeviceLock Service running on client computers automatically detects the connection state and seamlessly switches between online and offline mode every hour and when any of the following events occurs:

- A user boots the computer running DeviceLock Service. DeviceLock Service always starts in offline mode.
- A user logs on.
- A user right-clicks the DeviceLock Tray Notification Utility icon area in the notification area of the taskbar, and then clicks **Refresh Current State**.
   The DeviceLock Tray Notification Utility icon is displayed in the notification area when <u>Always show tray icon</u> is enabled in Service Options.
- DeviceLock Service sends audit and shadow logs to DeviceLock Enterprise Server.
- A network interface changes state:
  - A network cable is connected or disconnected.
  - A modem connects or disconnects.
  - A virtual private network (VPN) connection is established or terminated.
  - A wireless network connection using a Wi-Fi card is established or terminated.
  - A DHCP-assigned IP address is used or released.
  - A network card is enabled, disabled, added or removed.
- Changes to DeviceLock Service settings are made.

## **Managing Offline Security Policies for Devices**

You can manage offline security policies in much the same way as you manage online (regular) policies except for a few variations. This section provides offline profile-specific information as well as basic management procedures. For detailed information on Permissions, audit and shadowing rules, white lists, Content-Aware Rules, and Security

Settings for devices, refer to the following sections of the User Manual: "<u>Permissions</u> (<u>Regular Profile</u>)", "<u>Auditing & Shadowing (Regular Profile</u>)", "<u>USB Devices White List</u> (<u>Regular Profile</u>)", "<u>Media White List (Regular Profile</u>)", "<u>Security Settings (Regular Profile</u>)", "<u>Content-Aware Rules for Devices (Regular Profile</u>)."

Managing offline security policies for devices involves the following operations:

- Managing offline Permissions
- Managing offline audit and shadowing rules
- Managing the offline USB Devices White List
- Managing the offline Media White List
- Managing offline Content-Aware Rules
- Managing offline Security Settings

You can manage offline security policies by using DeviceLock Management Console, Service Settings Editor, or DeviceLock Group Policy Manager.

## **Managing Offline Permissions**

For a detailed description of the Permissions feature, see "Permissions (Regular Profile)."

Offline permissions can have one of the following states:

STATE	DESCRIPTION
Not Configured	Indicates that permissions on a device type are not set. This is the default state.
Configured	Indicates that permissions on a device type are set.
Full Access	Indicates that full access rights are granted to the Everyone account.
No Access	<ul> <li>Indicates one of the following:</li> <li>The Everyone account has No Access permissions and is the only account assigned to a device type. No Access permissions assigned to the Everyone account take priority over permissions assigned to other accounts.</li> <li>All users and groups assigned to a device type have No Access permissions.</li> <li>All users and groups assigned to a device type are removed.</li> </ul>

STATE	DESCRIPTION
Use Regular	Indicates that the inheritance of offline permissions is blocked and regular permissions are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.
	The enforcement of regular permissions is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular permissions lets you prevent offline permissions inherited from a higher level from being applied to a specific group of client computers at a lower level.
	For more information on the enforcement of regular permissions, see " <u>Removing</u> <u>Offline Permissions</u> ."

Managing offline permissions involves the following tasks:

- Setting and editing offline permissions
- Undefining offline permissions
- Removing offline permissions

## **Setting and Editing Offline Permissions**

#### To set and edit offline permissions

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, select **Permissions**.

When you select Permissions in the console tree, in the details pane you can view device types for which you can set permissions. In the details pane, you can also view the current state of offline permissions for each device type in the Offline column.

- 4. In the details pane, do one of the following:
  - Right-click the device type for which you want to set or edit permissions, and then click **Set Offline Permissions**.
    - OR -

 Select the device type for which you want to set or edit permissions, and then click Set Offline Permissions & on the toolbar.

Users	1		C						-	ł				
Not Configured			12 *	2 .	• 4	 5 *	8 .	• 10	* 12		 4 *	6	* 2	10 *
		All												
		Sunday												
add	Dalata Sat Dafarit	Monday												
Liter's Rights	Alow	Tuesday												
Generic		Wednesday												
Write	E I	Thursday												
Eject	H	Friday												
Read	B	Saturday												
Format	H													

The Permissions (Offline) dialog box appears.

5. In the **Permissions (Offline)** dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS
To set the default	<ul> <li>In the upper-left pane of the dialog box, under Users, click Set Default.</li> </ul>
permissions	The default permissions are assigned to the Administrators, Everyone, and SYSTEM accounts. For information about which permissions are set for these accounts by default, see " <u>Permissions (Regular Profile)</u> ."
To set	1. In the upper-left pane of the dialog box, under <b>Users</b> , click <b>Add</b> .
permissions for	The Select Users or Groups dialog box appears.
an additional user or group	<ol> <li>In the Select Users or Groups dialog box, in the Enter the object names to select box, type the name of the user or group, and then click OK.</li> </ol>
	The users and groups that you added are displayed under Users in the upper-left pane of the Permissions (Offline) dialog box.
	<ol><li>In the upper-left pane of the <b>Permissions (Offline)</b> dialog box, under <b>Users</b>, select the user or group.</li></ol>
	You can select multiple users and/ or groups by holding down the SHIFT key or the CTRL key while clicking them.
	<ol> <li>In the lower-left pane of the <b>Permissions (Offline)</b> dialog box, under <b>User's Rights</b>, select or clear the <b>Allow</b> check box next to the appropriate access rights.</li> </ol>
	In the right pane of the Permissions (Offline) dialog box, you can set day and time restrictions that narrow user access to devices.

TO DO THIS	FOLLOW THESE STEPS
	Use the left mouse button to select days and hours when the selected user or group will have access to devices. Use the right mouse button to mark days and hours when the selected user or group will not have access to devices.
To change	<ol> <li>In the upper-left pane of the dialog box, under Users, select the user or group.</li> </ol>
an existing user or group	<ol> <li>In the lower-left pane of the dialog box, under User's Rights, select or clear the Allow check box next to the appropriate access rights.</li> </ol>
To remove an existing user or group and permissions	<ul> <li>In the upper-left pane of the dialog box, under Users, select the user or group, and then click Delete or press the DELETE key.</li> </ul>

6. Click **OK** or **Apply**.

#### **Undefining Offline Permissions**

You can reset previously set offline permissions to the unconfigured state. If offline permissions are undefined, regular permissions are applied to offline client computers.

#### To undefine offline permissions

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, select **Permissions**.

When you select Permissions in the console tree, in the details pane you can view device types for which you can set permissions. In the details pane you can also view the current state of offline permissions for each device type in the Offline column.

4. In the details pane, right-click the device type for which you want to undefine offline permissions, and then click **Undefine Offline**.

*You can undefine offline permissions set for several device types at the same time. To do this, do the following:* 

- a) In the details pane, select several device types by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Undefine Offline**.

The offline state of the permissions changes to "Not Configured."

### **Removing Offline Permissions**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline permissions and enforce regular permissions on specific lower-level groups of client computers. To enforce regular permissions, you must remove offline permissions.

#### To remove offline permissions

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, select **Permissions**.

When you select Permissions in the console tree, in the details pane you can view device types for which you can set permissions. In the details pane you can also view the current state of offline permissions for each device type in the Offline column.

4. In the details pane, right-click the device type for which you want to remove offline permissions, and then click **Remove Offline**.

You can remove offline permissions set for several device types at the same time. To do this, do the following:

- a) In the details pane, select several device types by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection and then click **Remove Offline**.

The offline state of the permissions changes to "Use Regular."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

## **Managing Offline Audit and Shadowing Rules**

For a detailed description of the Auditing & Shadowing feature, see "<u>Auditing & Shadowing</u> (<u>Regular Profile</u>)."

Offline audit and shadowing rules can have one of the following states:
STATE	DESCRIPTION
Not Configured	Indicates that audit and shadowing rules are not defined for a device type. This is the default state.
Configured	Indicates that audit and shadowing rules are defined for a device type.
No Audit	<ul> <li>Indicates one of the following:</li> <li>Audit rights are not set for all of the users and groups specified in audit and shadowing rules for a device type</li> <li>All users and groups specified in audit and shadowing rules for a device type are removed.</li> <li>The Everyone account has no Audit and Shadowing rights and is the only account specified in audit and shadowing rules for a device type.</li> </ul>
Use Regular	Indicates that the inheritance of offline audit and shadowing rules is blocked and regular audit and shadowing rules are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager. The enforcement of regular rules is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular rules lets you prevent offline rules inherited from a higher level from being applied to a specific group of client computers at a lower level. For more information on the enforcement of regular rules, see " <u>Removing Offline</u> Audit and Shadowing Rules "

Managing offline audit and shadowing rules involves the following tasks:

- Defining and editing offline audit and shadowing rules
- Undefining offline audit and shadowing rules
- Removing offline audit and shadowing rules

# Defining and Editing Offline Audit and Shadowing Rules

#### To define and edit offline audit and shadowing rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.

- 2. Expand **Devices**.
- 3. Under **Devices**, select **Auditing & Shadowing**.

When you select Auditing & Shadowing in the console tree, in the details pane you can view device types for which you can define audit and shadowing rules. In the details pane you can also view the current state of offline rules for each device type in the Offline column.

- 4. In the details pane, do one of the following:
  - Right-click the device type for which you want to define or edit rules, and then click Set Offline Auditing & Shadowing.
     OR -
  - Select the device type for which you want to define or edit rules, and then click Set Offline Auditing & Shadowing 6 on the toolbar.

Users			¢					+						(
Not Configured			12 *	2	4 * 6	* 8	* 10	* 12	* 2	* 4	* 6	* 8	* 10	* 1
		Al	11					11						T
		Sunday												
Add	Delete Set Default	Monday												
ser's Rights	Allow	Tuesday												
Audit	-	Wednesday												
Read Write		Thursday												
Shadowing		Friday												
7119,0														

The Auditing & Shadowing (Offline) dialog box appears.

5. In the **Auditing & Shadowing (Offline)** dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS
To define the default audit and shadowing rules	<ol> <li>In the upper-left area of the dialog box, specify which events are written to the audit log. Select the <b>Audit Allowed</b> check box to audit successful attempts to gain access to a device. Select the <b>Audit Denied</b> check box to audit unsuccessful attempts to gain access to a device.</li> </ol>
	<ol> <li>In the upper-left pane of the dialog box, under Users, click Set Default.</li> </ol>
	The default audit and shadowing rules apply to members of the Users group and Everyone account. For information about which Audit and Shadowing rights are set for these accounts by default,

TO DO THIS	FOLLOW THESE STEPS
	see "Auditing & Shadowing (Regular Profile)."
To define audit and shadowing rules for an additional	<ol> <li>In the upper-left area of the dialog box, specify which events are written to the audit log. Select the <b>Audit Allowed</b> check box to audit successful attempts to gain access to a device. Select the <b>Audit Denied</b> check box to audit unsuccessful attempts to gain access to a device.</li> </ol>
user or group	2. In the upper-left pane of the dialog box, under <b>Users</b> , click <b>Add</b> .
	The Select Users or Groups dialog box appears.
	<ol> <li>In the Select Users or Groups dialog box, in the Enter the object names to select box, type the name of the user or group, and then click OK.</li> </ol>
	The users and groups that you added are displayed under Users in the upper-left pane of the Auditing & Shadowing (Offline) dialog box.
	<ol> <li>In the upper-left pane of the Auditing &amp; Shadowing (Offline) dialog box, under Users, select the user or group.</li> </ol>
	You can select multiple users and/ or groups by holding down the SHIFT key or the CTRL key while clicking them.
	<ol> <li>In the lower-left pane of the Auditing &amp; Shadowing (Offline) dialog box, under User's Rights, select or clear the Allow check box next to the appropriate audit and shadowing rights.</li> </ol>
	Audit and Shadowing rights determine which user actions on devices are logged to the audit and/or shadow log. In the right pane of the Auditing & Shadowing (Offline) dialog box, you can specify days and hours (for example, from 7 AM to 5 PM Monday through Friday) when the selected user's actions on devices will be logged to either the audit or shadow log. Use the left mouse button to select days and hours when the selected user's actions on devices will be logged. Use the right mouse button to mark days and hours when the selected user's actions on devices will not be logged.
To change audit and	<ol> <li>In the upper-left pane of the dialog box, under Users, select the user or group.</li> </ol>
shadowing rules for an existing user or group	<ol> <li>In the lower-left pane of the dialog box, under User's Rights, select or clear the Allow check box next to the appropriate audit and shadowing rights.</li> </ol>
To remove an existing user	<ul> <li>In the upper-left pane of the dialog box, under Users, select the user or group, and then click Delete or press the DELETE key.</li> </ul>
or group and rules	When you remove a user or group, any rules for that user or group will also be removed.

# 6. Click **OK** or **Apply**.

# **Undefining Offline Audit and Shadowing Rules**

You can return previously defined offline audit and shadowing rules to the unconfigured state. If offline rules are undefined, regular rules are applied to offline client computers.

# To undefine offline audit and shadowing rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under Devices, select Auditing & Shadowing.

When you select Auditing & Shadowing in the console tree, in the details pane you can view device types for which you can define audit and shadowing rules. In the details pane you can also view the current state of offline rules for each device type in the Offline column.

4. In the details pane, right-click the device type for which you want to undefine offline audit and shadowing rules, and then click **Undefine Offline**.

You can undefine audit and shadowing rules defined for several device types at the same time. To do this, do the following:

- a) In the details pane, select several device types by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click Undefine Offline. The offline state of the audit and shadowing rules changes to "Not Configured."

# **Removing Offline Audit and Shadowing Rules**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline audit and shadowing rules and enforce regular audit and shadowing rules on specific lower-level groups of client computers. To enforce regular audit and shadowing rules, you must remove offline audit and shadowing rules.

# To remove offline audit and shadowing rules

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.

# 2. Expand **Devices**.

3. Under **Devices**, select **Auditing & Shadowing**.

When you select Auditing & Shadowing in the console tree, in the details pane you can view device types for which you can define audit and shadowing rules. In the details pane you can also view the current state of offline rules for each device type in the Offline column.

4. In the details pane, right-click the device type for which you want to remove offline audit and shadowing rules, and then click **Remove Offline**.

You can remove audit and shadowing rules defined for several device types at the same time. To do this, do the following:

- a) In the details pane, select several device types by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Remove Offline**.

The offline state of the audit and shadowing rules changes to "Use Regular."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

# **Managing Offline USB Devices White List**

For a detailed description of the USB Devices White List feature, see "<u>USB Devices White</u> List (Regular Profile)."

STATE	DESCRIPTION
Not Configured	Indicates that the white list is not defined. The following message is displayed: "Offline USB White List is not configured." This is the default state.
Configured	Indicates that the white list is defined.
Use Regular	Indicates that the inheritance of the offline white list is blocked and the regular white list is enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.
	The enforcement of the regular white list is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of the regular white list lets you prevent the offline white list inherited from a higher level from being applied to a specific group of client computers at a lower level.
	For more information on the enforcement of the regular white list, see " <u>Removing</u> Offline USB Devices White List."

The offline USB Devices White List can have one of the following states:

Managing the offline USB Devices White List involves the following tasks:

- Defining and editing the offline USB Devices White List
- Exporting and importing the offline USB Devices White List

- Undefining the offline USB Devices White List
- Removing the offline USB Devices White List

#### Defining and Editing Offline USB Devices White List

#### To define and edit the offline USB Device White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click USB Devices White List, and then click Manage Offline.
     OR -
  - Select USB Devices White List, and then click Manage Offline 
     on the toolbar.

The USB Devices White List (Offline) dialog box appears.

📑 USB Devices White List (Offline)				? 🛛
USB Devices Database				
Description	DeviceID	Туре		
Add USB Devices Database			SPow:	All Types
USB Devices White List				
Users	Devices			
Users	Description	DeviceID	Reinitia	ize Contro
	<			>
Add Dejete	Dglete Edit		Lo	ad Soye
			OK Car	cel Apply

4. In the upper pane of the USB Devices White List (Offline) dialog box, under USB Devices Database, click USB Devices Database.

	Available US8 Device	s (Local Computer):		
Description	DeviceID	Present		
Add Expand	Al Cglapse Al	Remote Computer	Show all devices	Refresh
Parasisting.	USB Devices	Database:		
Description	USB Devices DeviceID	Database:		
	DeviceID	Туре		
Dglete Edg		Show: All Types	V Load	Saye

The USB Devices Database dialog box appears.

*In the upper pane of the USB Devices Database dialog box, under Available USB Devices, you can view the devices that are currently plugged in.* 

To view all devices ever plugged into USB ports on the computer, click **Show all devices**. To view available devices on a remote computer, click **Remote Computer**.

The Remote Computer button is unavailable when the management console is connected to the local computer.

5. In the upper pane of the **USB Devices Database** dialog box, under **Available USB Devices**, select the device you want to add to the USB Devices White List, and then click **Add**.

The device that you added is displayed under USB Devices Database in the lower pane of the dialog box.

**Note:** You can add a device to the USB Devices White List only after you add this device to the USB Devices Database.

The same USB Devices Database is used for both the regular and offline USB Devices White List.

To delete a device from the USB Devices Database, in the lower pane of the **USB Devices Database** dialog box, under **USB Devices Database**, do one of the following:

- Select the device, and then click **Delete**.
   OR -
- Right-click the device, and then click **Delete**.

*Devices are not deleted automatically from the white list after you delete them from the USB Devices Database.* 

To edit a device's description, in the lower pane of the **USB Devices Database** dialog box, under **USB Devices Database**, select the device, and then click **Edit**.

If you change a device's description in the USB Database, the following behavior occurs: The device will have its old description in the white list if it has already been added to the white list.

6. Click **OK** or **Apply**.

The device that you added to the USB Devices Database is displayed under USB Devices Database in the upper pane of the USB Devices White List (Offline) dialog box.

7. In the lower-left pane of the **USB Devices White List (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

 In the Select Users or Groups dialog box, in the Enter the object names to select box, type the names of the users or groups for which you want to define the USB Devices White List, and then click OK.

The users and groups that you added are displayed under Users in the lower-left pane of the USB Devices White List (Offline) dialog box.

To delete a user or group, in the lower-left pane of the **USB Devices White List (Offline)** dialog box, under **Users**, select the user or group, and then click **Delete** or press the DELETE key.

9. In the lower-left pane of the **USB Devices White List (Offline)** dialog box, under **Users**, select the user or group.

You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

10. In the upper pane of the **USB Devices White List (Offline)** dialog box, under **USB Devices Database**, select the device you want to add to the white list for the selected user or group, and then click **Add**.

You can select multiple devices by holding down the SHIFT key or the CTRL key while clicking them.

The devices that you added to the white list are displayed under Devices in the lower-right pane of the dialog box.

To delete a device from the white list for the selected user or group, in the lowerright pane of the **USB Devices White List (Offline)** dialog box, under **Devices**, do the following:

• Select the device, and then click **Delete**.

- OR -

- Right-click the device, and then click **Delete**.
   OR -
- Select the device, and then press the DELETE key.

To edit a device's description, in the lower-right pane of the **USB Devices White List (Offline)** dialog box, under **Devices**, do the following:

- Select the device, and then click Edit.
   OR -
- Right-click the device, and then click **Edit**.

11. Click **OK** or **Apply**.

#### Exporting and Importing Offline USB Devices White List

You can export the offline USB Devices White List to a .whl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

#### To export the offline USB Devices White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click USB Devices White List, and then click Save Offline.
     OR -
  - Select USB Devices White List, and then click Save Offline 
     on the toolbar.
    - OR -
  - Expand USB Devices White List, right-click any user or group specified in the white list, and then click Save Offline.
     OR -
  - Expand **USB Devices White List**, select any user or group specified in the white list. In the details pane, right-click the white listed device, and then click **Save**.
    - OR -
  - Right-click USB Devices White List, and then click Manage Offline. In the lower-right pane of the USB Devices White List (Offline) dialog box, under Devices, click Save.

The Save As dialog box appears.

- 4. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .whl file.
- 5. In the **File name** box, type the file name you want.

6. Click **Save**.

When you export the offline USB Devices White List, it is saved in a file with a .whl extension.

#### To import the offline USB Devices White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click USB Devices White List, and then click Load Offline.
     OR -
  - Select USB Devices White List, and then click Load Offline is on the toolbar.

- OR -

- Expand USB Devices White List, right-click any user or group specified in the white list, and then click Load Offline.
  - OR -
- Expand **USB Devices White List**, and then select any user or group specified in the white list. In the details pane, right-click the white listed device, and then click **Load**.

- OR -

• Right-click **USB Devices White List**, and then click **Manage Offline**. In the lower-right pane of the **USB Devices White List (Offline)** dialog box, under **Devices**, click **Load**.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open**.

# **Undefining Offline USB Devices White List**

You can return the previously defined offline white list to the unconfigured state. If the offline white list is undefined, the regular white list is applied to offline client computers.

# To undefine the offline USB Devices White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, right-click **USB Devices White List**, and then click **Undefine Offline**.

The offline state of the white list changes to "Not Configured."

When you select **USB Devices White List** in the console tree, in the details pane the following message is displayed: "Offline USB White List is not configured."

#### **Removing Offline USB Devices White List**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of the higher-level offline white list and enforce the regular white list on specific lower-level groups of client computers. To enforce the regular USB Devices White List, you must remove the offline USB Devices White List.

# To remove the offline USB Devices White List

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, right-click **USB Devices White List**, and then click **Remove Offline**.

The offline state of the white list changes to "Use Regular."

When you select **USB Devices White List** in the console tree, in the details pane the following message is displayed: "Offline USB White List is configured to use Regular USB White List.

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

# **Managing Offline Media White List**

For a detailed description of the Media White List feature, see "<u>Media White List (Regular</u> <u>Profile)</u>."

The offline Media White List can have one of the following states:

STATE	DESCRIPTION
Not Configured	Indicates that the white list is not defined. The following message is displayed: "Offline Media White List is not configured." This is the default state.
Configured	Indicates that the white list is defined.
Use Regular	Indicates that the inheritance of the offline white list is blocked and the regular white list is enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.
	The enforcement of the regular white list is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of the regular white list lets you prevent the offline white list inherited from a higher level from being applied to a specific group of client computers at a lower level.
	For more information on the enforcement of the regular white list, see " <u>Removing</u> Offline Media White List."

Managing the offline Media White List involves the following tasks:

- Defining and editing the offline Media White List
- Exporting and importing the offline Media White List
- Undefining the offline Media White List
- Removing the offline Media White List

# Defining and Editing Offline Media White List

#### To define and edit the offline Media White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Media White List, and then click Manage Offline.
     OR -
  - Select **Media White List**, and then click **Manage Offline a** on the toolbar.

The Media White List (Offline) dialog box appears.

Media White List (Offline)			2
Media Database			
Description	MediaID	Туре	
Add Media Database			
Andra White List	_		
Users	Media		
Users	Description	MediaID	Туре
	<		>
Add Dejete	Dglete Edt		Load Save
		OK	Cancel Apply

4. In the upper pane of the **Media White List (Offline)** dialog box, under **Media Database**, click **Media Database**.

The Media Database dialog box appears.

	Drives:		
Drive	Type	Volume Name	
을D: (No Media) 을E: (No Media)	DVD/CD-ROM DVD/CD-ROM		
Add Eject	t Lgad MediatD	Туре	Refresh

*In the upper pane of the Media Database dialog box, under Drives, you can view all CD-ROM and DVD-ROM drives available on the local computer.* 

The list of drives is automatically refreshed and displays new media as soon as they arrive. To manually refresh this list, click **Refresh**.

5. In the upper pane of the **Media Database** dialog box, under **Drives**, select the drive that contains the media you want to add to the Media White List, and then click **Add**.

The selected media are added to the Media Database and can be viewed in the lower pane of the Media Database dialog box.

**Note:** You can add media to the Media White List only after you add the media to the Media Database.

The same Media Database is used for both the regular and offline Media White List.

To delete a medium from the white list, in the lower pane of the **Media Database** dialog box, do the following:

- Select the medium, and then click **Delete**.
   OR -
- Right-click the medium, and then click **Delete**.

To edit a medium's description, in the lower pane of the **Media Database** dialog box, select the medium, and then click **Edit**.

6. Click **OK** or **Apply**.

The media that you added to the Media Database are displayed under Media Database in the upper pane of the Media White List (Offline) dialog box.

7. In the lower-left pane of the **Media White List (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

8. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups for which you want to define the Media White List, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Media White List (Offline) dialog box.

To delete a user or group, in the lower-left pane of the **Media White List (Offline)** dialog box, under **Users**, select the user or group, and then click **Delete** or press the DELETE key.

9. In the lower-left pane of the **Media White List (Offline)** dialog box, under **Users**, select the user or group.

You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

10. In the upper pane of the **Media White List (Offline)** dialog box, under **Media Database**, select the medium you want to add to the white list for the selected user or group, and then click **Add**.

You can select multiple media by holding down the SHIFT key or the CTRL key while clicking them.

The media that you added to the white list are displayed under Media in the lowerright pane of the dialog box.

To delete a medium from the white list for the selected user or group, in the lowerright pane of the **Media White List (Offline)** dialog box, under **Media**, do the following:

- Select the medium, and then click **Delete**.
   OR -
- Right-click the medium, and then click **Delete**.

To edit a medium's description for the selected user or group, in the lower-right pane of the **Media White List (Offline)** dialog box, under **Media**, do the following:

- Select the medium, and then click Edit.
   OR -
- Right-click the medium, and then click **Edit**.

#### 11. Click **OK** or **Apply**.

#### Exporting and Importing Offline Media White List

You can export the offline Media White List to a .mwl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

#### To export the offline Media White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Media White List, and then click Save Offline.
     OR -
  - Select Media White List, and then click Save Offline 
     OR -
  - Expand **Media White List**, right-click any user or group specified in the white list, and then click **Save Offline**.
    - OR -
  - Expand **Media White List**, and then select any user or group specified in the white list. In the details pane, right-click the white listed medium, and then click **Save**.
    - OR -
  - Right-click **Media White List**, and then click **Manage Offline**. In the lowerright pane of the **Media White List (Offline)** dialog box, under **Media**, click **Save**.

The Save As dialog box appears.

- 4. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .mwl file.
- 5. In the **File name** box, type the file name you want.
- 6. Click **Save**.

When you export the offline Media White List, it is saved in a file with a .mwl extension.

# To import the offline Media White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.

- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Media White List, and then click Load Offline.
     OR -
  - Select Media White List, and then click Load Offline is on the toolbar.
     OR -
  - Expand **Media White List**, right-click any user or group specified in the white list, and then click **Load Offline**.
    - OR -
  - Expand **Media White List**, and then select any user or group specified in the white list. In the details pane, right-click the white listed device, and then click **Load**.
    - OR -
  - Right-click **Media White List**, and then click **Manage Offline**. In the lowerright pane of the **Media White List (Offline)** dialog box, under **Media**, click **Load**.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open**.

# Undefining Offline Media White List

You can return the previously defined offline white list to the unconfigured state. If the offline white list is undefined, the regular white list is applied to offline client computers.

# To undefine the offline Media White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, right-click **Media White List**, and then click **Undefine Offline**.

The offline state of the white list changes to "Not Configured."

When you select **Media White List** in the console tree, in the details pane the following message is displayed: "Offline Media White List is not configured."

# **Removing Offline Media White List**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of the higher-level offline white list and enforce the regular white list on specific lower-level groups of client computers. To enforce the regular Media White List, you must remove the offline Media White List.

# To remove the offline Media White List

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, right-click **Media White List**, and then click **Remove Offline**.

The offline state of the white list changes to "Use Regular."

When you select **Media White List** in the console tree, in the details pane the following message is displayed: "Offline Media White List is configured to use Regular Media White List.

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

# **Managing Offline Content-Aware Rules for Devices**

For a detailed description of the Content-Aware Rules feature for devices, see "<u>Content-</u> Aware Rules for Devices (Regular Profile)."

STATE	DESCRIPTION
Not Configured	Indicates that Content-Aware Rules are not defined. The following message is displayed: "Offline Content-Aware Rules are not configured." This is the default state.
Configured	Indicates that Content-Aware Rules are defined.
Use Regular	Indicates that the inheritance of offline Content-Aware Rules is blocked and regular Content-Aware Rules are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.

The offline Content-Aware Rules can have one of the following states:

STATE	DESCRIPTION
	The enforcement of regular Content-Aware Rules is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular Content-Aware Rules lets you prevent offline Content-Aware Rules inherited from a higher level from being applied to a specific group of client computers at a lower level.
	For more information on the enforcement of regular Content-Aware Rules, see "Removing Offline Content-Aware Rules."

Managing offline Content-Aware Rules involves the following tasks:

- Defining offline Content-Aware Rules
- Editing offline Content-Aware Rules
- Copying offline Content-Aware Rules
- Exporting and importing offline Content-Aware Rules
- Deleting offline Content-Aware Rules
- Undefining offline Content-Aware Rules
- Removing offline Content-Aware Rules

#### **Defining Offline Content-Aware Rules**

Content-Aware Rules are created based on either the built-in or custom content groups. For detailed information on these groups, see "<u>Configuring Content Detection Settings</u>."

# To define an offline Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage Offline.
     OR -
  - Select Content-Aware Rules, and then click Manage Offline 
     on the toolbar.

The Content-Aware Rules (Offline) dialog box appears.

🗠 Content-Aware Rules (Offline)						2 🗙
Content Database						
Description				Type		^
ABA Routing Number				Pattern (	buit-in)	
R Acquisition				Keyword	s (built-in)	
Admission Discharge			Keyword	s (built-in)		
Adult Keywords	Adult Keywords			Keyword	Keywords (built-in)	
American Address				Keyword	Keywords (built-in)	
American Name				Keyword	Keywords (built-in)	
Archives				File Type	Detection (built-in)	
Rack ARA				Kerword	He Type Detection (built-in)	
- Connon				neymord.	(concern)	<u> </u>
Add Test Group Dupl	cate Add G	roup • View	Group Delete Group	Show: All Ty	pes	~
Content-Aware Rules	Du las					
	Rules					_
Users A	Description	Type	Action(s)	Applies To	Protocol(s)	
			2			
Add Delete	Delete	Edit			Load Save	
				ОК	Cancel	ophy

4. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

5. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups for which you want to define the rule, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules (Offline) dialog box.

To delete a user or group, in the lower-left pane of the **Content-Aware Rules** (Offline) dialog box, under **Users**, select the user or group, and then click **Delete** or press the DELETE key.

6. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the users or groups for which you want to define the rule.

*You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.* 

7. In the upper pane of the **Content-Aware Rules (Offline)** dialog box, under **Content Database**, select the desired content group, and then click **Add**.

**Note:** You can specify only one content group for a Content-Aware Rule.

The Add Rule dialog box appears.

a Add Rule	20
Description: Credit Card Num	ber
Applies to	
Permissions Shadowin	9
Devices Type(s):	
Actions	
Actions	Allow Denv
Actions User's Rights	Allow Deny

8. In the **Add Rule** dialog box, in the **Description** box, type the name of the Content-Aware Rule.

By default, the Content-Aware Rule has the same name as the specified content group but you can enter a different name.

- 9. **Under Applies to**, specify the type of operation associated with the rule. The available options are:
  - **Permissions**: Specifies that the rule will apply to access control operations.
  - **Shadowing**: Specifies that the rule will apply to shadow copy operations.
  - **Permissions**, **Shadowing**: Specifies that the rule will apply to both access control and shadow copy operations.
- 10. Under **Device Type(s)**, select the appropriate device type(s) you would like this rule to be applied to.

*Content-Aware Rules can be applied to the DVD/CD-ROM, Floppy, iPhone, Palm, Removable, and Windows Mobile device types.* 

11. Under **Action(s)**, specify which user actions are allowed or disallowed on files and which user actions are logged to the shadow log.

You can select any of the following options: Read, Write, Read and Write.

If the rule applies to shadow copy operations or both access control and shadow copy operations, the Read option becomes unavailable. For detailed information on user rights that can be specified in Content-Aware Rules, see "<u>Content-Aware Rules</u> for Access Control Operations" and "<u>Content-Aware Rules for Shadow Copy</u> <u>Operations</u>."

12. Click **OK**.

The rule you created is displayed under Rules in the lower-right pane of the Content-Aware Rules (Offline) dialog box. 13. Click **OK** or **Apply** to apply the rule.

The users or groups to which the Content-Aware Rule applies are displayed under Content-Aware Rules in the console tree.

When you select a user or group to which a Content-Aware Rule applies in the console tree, in the details pane you can view detailed information regarding this rule. This information includes the following:

- **Description** The name of the rule. By default, the rule has the same name as the specified content group.
- Type The type of the content analysis. Possible values: File Type Detection, Keywords, Pattern, Document Properties, and Complex. File Type Detection indicates that recognition and identification of files is based on their characteristic signatures. Keywords indicates that recognition and identification of data/files is based on the specified keywords or phrases.
   Pattern indicates that recognition and identification of data/files is based on the specified patterns of text described by Perl regular expressions.
   Document Properties indicates that recognition and identification of files is based on their properties. Complex indicates that recognition and identification of data/files is based on the specified content described by a Boolean expression.
- Action(s) Shows which user actions are allowed or disallowed on files and which user actions are logged to the shadow log.
- Applies To Possible values: Permissions, Shadowing, and Permissions, Shadowing. Permissions indicates that the rule applies to access control operations. Shadowing indicates that the rule applies to shadow copy operations. Permissions, Shadowing indicates that the rule applies to both access control and shadow copy operations.
- **Device Type(s)** The device type(s) to which the rule applies.
- **Profile** Possible values: **Regular** and **Offline**. **Regular** indicates that the rule applies to client computers that are working online. **Offline** indicates that the rule applies to computers that are working offline.

You can define different online vs. offline Content-Aware Rules for the same user or sets of users. For information about how to define online Content-Aware Rules, see "<u>Managing Content-Aware Rules</u>."

# **Editing Offline Content-Aware Rules**

You can modify the Content-Aware Rule properties such as Description, Applies To, Device Type(s), Actions.

# To edit an offline Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, right-click **Content-Aware Rules**, click **Manage Offline**, and then do the following:
  - a) In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the user or group for which you want to edit the rule. *By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.*
  - b) In the lower-right pane of the Content-Aware Rules (Offline) dialog box, under Rules, select the rule you want to edit, and then click Edit.
     OR -

Right-click the rule, and then click **Edit**.

- OR -

Under **Devices**, expand **Content-Aware Rules**, and then do the following:

a) Under **Content-Aware Rules**, select the user or group for which you want to edit the rule.

*By selecting users or groups, you can view the Content-Aware Rules applied to them in the details pane.* 

b) In the details pane, right-click the rule you want to edit, and then click **Edit**.

The Edit Rule dialog box appears.

- 4. In the **Edit Rule** dialog box, modify the rule properties as required to meet your needs.
- 5. Click **OK** to apply the changes.

# **Copying Offline Content-Aware Rules**

You can perform a cut-and-paste operation, a copy-and-paste operation or a drag-and-drop operation to reuse existing offline Content-Aware Rules.

# To copy an offline Content-Aware Rule

1. If you use DeviceLock Management Console, do the following:

- a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.

- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage Offline.
     OR -
  - Select Content-Aware Rules, and then click Manage Offline and on the toolbar.

The Content-Aware Rules (Offline) dialog box appears.

4. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the user or group to which the rule that you want to copy is applied.

*By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.* 

5. In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, under **Rules**, right-click the rule you want to copy, and then click **Copy** or **Cut**.

The rule you cut or copy is automatically copied to the Clipboard.

You can use the CTRL+C, CTRL+X and CTRL+V key combinations to copy, cut and paste the rule. When you cut the rule, the rule will be cut only after you paste it.

To perform a drag-and-drop operation, select the rule and move it to the user or group to which you want to apply the copied rule.

6. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

7. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups to which you want to apply the copied rule, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules (Offline) dialog box.

8. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the users or groups for which you want to set permissions.

You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

9. In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, rightclick in the **Rules** pane and then click **Paste**.

The copied rule is displayed under Rules in the lower-right pane of the Content-Aware Rules (Offline) dialog box.

10. Click **OK** or **Apply** to apply the copied rule.

# **Exporting and Importing Offline Content-Aware Rules**

You can export all your current offline Content-Aware Rules to a .cwl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

#### To export offline Content-Aware Rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Save Offline.
     OR -
  - Select Content-Aware Rules, and then click Save Offline 
     on the toolbar.
    - OR -
  - Expand **Content-Aware Rules**, right-click any user or group, and then click **Save Offline**.
    - OR -
  - Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Save**.
    - OR -
  - Expand Content-Aware Rules, select any user or group to which the rule is applied, and then click Save Offline Source on the toolbar.
     OR -
  - Right-click Content-Aware Rules, and then click Manage (Offline). In the lower-right pane of the Content-Aware Rules (Offline) dialog box, under Rules, click Save.

The Save As dialog box appears.

- 4. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .cwl file.
- 5. In the **File name** box, type the file name you want.
- 6. Click Save.

When you export rules, they are saved in a file with a .cwl extension.

#### **To import offline Content-Aware Rules**

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Content-Aware Rules, and then click Load Offline.
     OR -
  - Select Content-Aware Rules, and then click Load Offline is on the toolbar.

- OR -

• Expand **Content-Aware Rules**, right-click any user or group, and then click **Load Offline**.

- OR -

- Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Load**.
  - OR -
- Expand Content-Aware Rules, select any user or group to which the rule is applied, and then click Load Offline and the toolbar.
   OR -
- Right-click **Content-Aware Rules**, and then click **Manage Offline**. In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, under **Rules**, click **Load**.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open**.

You can import only one .cwl file at a time.

# **Deleting Offline Content-Aware Rules**

You can delete individual offline Content-Aware Rules when they are no longer required.

#### To delete an offline Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**,
- 3. Under **Devices**, do one of the following:
  - Expand **Content-Aware Rules**, right-click the user or group to which the rule is applied, and then click **Delete user**. When you delete a user or group, the rule associated with this user or group is automatically deleted.

- OR -

• Expand **Content-Aware Rules**, and then select the user or group to which the rule is applied. In the details pane, right-click the rule associated with this user or group, and then click **Delete**.

- OR -

Right-click Content-Aware Rules, and then click Manage Offline. In the lower-left pane of the Content-Aware Rules (Offline) dialog box, under Users, select the user or group to which the rule is applied. In the lower-right pane of the Content-Aware Rules (Offline) dialog box, under Rules, select the rule, and then click Delete or right-click the rule, and then click Delete. You can select multiple rules that you want to delete by holding down the SHIFT key or the CTRL key while clicking them.

# **Undefining Offline Content-Aware Rules**

You can return the previously defined offline Content-Aware Rules to the unconfigured state. If offline rules are undefined, regular rules are applied to offline client computers.

# To undefine offline Content-Aware Rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under Devices, right-click Content-Aware Rules, and then click Undefine Offline.

The offline state of Content-Aware Rules changes to "Not Configured."

When you select **Content-Aware Rules** in the console tree, in the details pane the following message is displayed: "Offline Content-Aware Rules are not configured."

# **Removing Offline Content-Aware Rules**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline Content-Aware Rules and enforce regular Content-Aware Rules on specific lower-level groups of client computers. To enforce regular Content-Aware Rules, you must remove offline Content-Aware Rules.

#### To remove offline Content-Aware Rules

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under Devices, right-click Content-Aware Rules, and then click Remove Offline.

The offline state of Content-Aware Rules changes to "Use Regular."

When you select **Content-Aware Rules** in the console tree, in the details pane the following message is displayed: "Offline Content-Aware Rules are configured to use Regular Content-Aware Rules."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

# **Managing Offline Security Settings**

For a detailed description of the Security Settings feature, see "<u>Security Settings (Regular</u> <u>Profile</u>)."

Offline Security Settings can have one of the following states:

STATE	DESCRIPTION
Not Configured	Indicates that Security Settings are not defined. This is the default state.
Enabled	Indicates that Security Settings are defined to enable audit and access control for the specified device classes.
Disabled	Indicates that Security Settings are defined to disable audit and access control for the specified device classes.
Use Regular	Indicates that the inheritance of offline Security Settings is blocked and regular Security Settings are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.
	The enforcement of regular Security Settings is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular Security Settings lets you prevent offline Security Settings inherited from a higher level from being applied to a specific group of client computers at a lower level.
	For more information on the enforcement of regular Security Settings, see " <u>Removing Offline Security Settings</u> ."

Managing offline Security Settings involves the following tasks:

- Defining and changing offline Security Settings
- Undefining offline Security Settings
- Removing offline Security Settings

# **Defining and Changing Offline Security Settings**

Offline Security Settings can be defined and changed individually or collectively.

# To define and change offline Security Settings individually

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under Devices, select Security Settings.

When you select Security Settings in the console tree, they are displayed in the details pane.

4. In the details pane, right-click any Security Setting, and then click **Enable Offline**.

The Security Setting changes its offline state from "Not Configured" to "Enabled."

Once you have enabled a particular Security Setting, you can disable it. To do so, right-click the enabled Security Setting, and then click **Disable Offline**.

The Security Setting changes its offline state from "Enabled" to "Disabled."

# To define and change offline Security Settings collectively

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Security Settings, and then click Manage Offline.
     OR -
  - Select Security Settings, and then click Manage Offline 
    on the toolbar.
     OR -
  - Select Security Settings. In the details pane, right-click any Security Setting, and then click Manage Offline.
     OR –
  - Select **Security Settings**. In the details pane, select any Security Setting, and then click **Manage Offline** on the toolbar.

When you select Security Settings in the console tree, they are displayed in the details pane.

The Security Settings (Offline) dialog box appears.

Access control	for USB HID (mouse, key	board, etc.)
Access control	for USB printers	
Access control	for USB Bluetooth adapte	rs
Access control	for USB and FireWire net	work cards
Access control	for USB scanners and stil	l image devices
Access control	for serial modems (intern	al & external)
Access control	for USB storage devices	
Access control	for virtual DVD/CD-ROMs	(Windows 2000 and later)
Access control	for FireWire storage devi	ces
Access control	for virtual printers (Winde	ows 2000 and later)

4. In the **Security Settings (Offline)** dialog box, select the appropriate check boxes for the Security Settings that you want to define.

Once you have enabled Security Settings, you can disable them. To do so, clear the appropriate check boxes.

**Note:** All check boxes in the **Security Settings (Offline)** dialog box have three states: selected, cleared, and indeterminate that correspond to the Enabled, Disabled, and Not Configured states of Security Settings.

5. Click **OK**.

# **Undefining Offline Security Settings**

You can return the previously defined offline Security Settings to the unconfigured state. If offline Security Settings are undefined, regular Security Settings are applied to offline client computers. You can undefine Security Settings individually or collectively.

#### To undefine offline Security Settings individually

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under Devices, select Security Settings.

When you select Security Settings in the console tree, they are displayed in the details pane.

4. In the details pane, right-click any Security Setting you want to undefine, and then click **Undefine Offline**.

The Security Setting changes its offline state to "Not Configured."

#### To undefine offline Security Settings collectively

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, do one of the following:
  - Right-click Security Settings, and then click Manage Offline.
     OR –
  - Select Security Settings, and then click Manage Offline 
    on the toolbar.
     OR -
  - Select Security Settings. In the details pane, right-click any Security Setting, and then click Manage Offline.
     OR –
  - Select **Security Settings**. In the details pane, select any Security Setting, and then click **Manage Offline** on the toolbar.

When you select Security Settings in the console tree, they are displayed in the details pane.

The Security Settings (Offline) dialog box appears.

4. In the **Security Settings (Offline)** dialog box, return the appropriate check boxes to the indeterminate state.

**Note:** All check boxes in the Security Settings (Offline) dialog box have three states: selected, cleared, and indeterminate that correspond to the Enabled, Disabled, and Not Configured states of Security Settings.

#### **Removing Offline Security Settings**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline Security Settings and enforce regular Security Settings on specific lower-level groups

of client computers. To enforce regular Security Settings, you must remove offline Security Settings. You can remove only individual Security Settings.

# To remove offline Security Settings

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Devices**.
- 3. Under **Devices**, select **Security Settings**.

When you select Security Settings in the console tree, they are displayed in the details pane.

4. In the details pane, right-click any Security Setting you want to remove, and then click **Remove Offline**.

The Security Setting changes its offline state to "Use Regular."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

# Managing Offline Security Policies for Protocols

Managing offline security policies for protocols involves the following operations:

- Managing offline Permissions for protocols
- Managing offline audit and shadowing rules for protocols
- Managing the offline Protocols White List
- Managing offline Content-Aware Rules for protocols
- Managing offline Security Settings for protocols

# **Managing Offline Permissions for Protocols**

For a detailed description of the Permissions feature for protocols, see "<u>Managing</u> <u>Permissions for Protocols</u>."

Offline permissions can have one of the following states:

STATE	DESCRIPTION
Not Configured	Indicates that permissions on a protocol are not set. This is the default state.
Configured	Indicates that permissions on a protocol are set.

STATE	DESCRIPTION
Full Access	Indicates that full access rights are granted to the Everyone account.
No Access	<ul> <li>Indicates one of the following:</li> <li>The Everyone account has No Access permissions and is the only account assigned to a protocol. No Access permissions assigned to the Everyone account take priority over permissions assigned to other accounts.</li> <li>All users and groups assigned to a protocol have No Access permissions.</li> <li>All users and groups assigned to a protocol are removed.</li> </ul>
Use Regular	<ul> <li>Indicates that the inheritance of offline permissions is blocked and regular permissions are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.</li> <li>The enforcement of regular permissions is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular permissions lets you prevent offline permissions inherited from a higher level from being applied to a specific group of client computers at a lower level.</li> <li>For more information on the enforcement of regular permissions, see "<u>Removing Offline Permissions</u>."</li> </ul>

Managing offline permissions involves the following tasks:

- Setting and editing offline permissions
- Undefining offline permissions
- Removing offline permissions

#### **Setting and Editing Offline Permissions**

#### To set and edit offline permissions

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under Protocols, select Permissions.

When you select Permissions in the console tree, in the details pane you can view protocols for which you can set permissions. In the details pane, you can also view the current state of offline permissions for each protocol in the Offline column.

- 4. In the details pane, do one of the following:
  - Right-click the protocol for which you want to set or edit permissions, and then click Set Offline Permissions.
     - OR -
  - Select the protocol for which you want to set or edit permissions, and then click Set Offline Permissions on the toolbar.

🖧 Permissions (Offline) ? 🗙 Protocol(s): FTP Computer Name: Local Computer 書 Users Not Configured \* 6 \* 8 \* 10 \* 12 \* 2 \* 4 . = 10 = 12 Add Set Default User's Rights Allow Generic Send/Receive Data **Outgoing Files** SSL Send/Receive Data Outgoing Files III - Allowed Time III - Denied Time Protocols White List Cancel

The Permissions (Offline) dialog box appears.

5. In the **Permissions (Offline)** dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS
To set the default permissions	<ul> <li>In the upper-left pane of the dialog box, under Users, click Set Default.</li> <li>The default permissions are assigned to the Administrators and Everyone accounts. For information about which permissions are set for these accounts by default, see "Managing Permissions for Protocols."</li> </ul>
To set permissions for an additional user or group	1. In the upper-left pane of the dialog box, under Users, click Add.
	The Select Users or Groups dialog box appears.
	<ol> <li>In the Select Users or Groups dialog box, in the Enter the object names to select box, type the name of the user or group, and then click OK.</li> </ol>
	The users and groups that you added are displayed under Users in the upper-left pane of the Permissions (Offline) dialog box.

TO DO THIS	FOLLOW THESE STEPS		
	<ol> <li>In the upper-left pane of the <b>Permissions (Offline)</b> dialog box, under <b>Users</b>, select the user or group.</li> </ol>		
	You can select multiple users and/ or groups by holding down the SHIFT key or the CTRL key while clicking them.		
	<ol> <li>In the lower-left pane of the <b>Permissions (Offline)</b> dialog box, under <b>User's Rights</b>, select or clear the <b>Allow</b> check box next to the appropriate access rights.</li> </ol>		
	In the right pane of the Permissions (Offline) dialog box, you can set day and time restrictions that narrow user access to the specified protocol(s). Use the left mouse button to select days and hours when the selected user or group will have access to the specified protocol(s). Use the right mouse button to mark days and hours when the selected user or group will not have access to the specified protocol(s).		
To change permissions for	<ol> <li>In the upper-left pane of the dialog box, under Users, select the user or group.</li> </ol>		
an existing user or group	<ol> <li>In the lower-left pane of the dialog box, under User's Rights, select or clear the Allow check box next to the appropriate access rights.</li> </ol>		
To remove an existing user or	<ul> <li>In the upper-left pane of the dialog box, under Users, select the user or group, and then click Delete or press the DELETE key.</li> </ul>		
group and permissions	When you remove a user or group, any permissions for that user or group will also be removed.		

6. Click **OK** or **Apply**.

# **Undefining Offline Permissions**

You can reset previously set offline permissions to the unconfigured state. If offline permissions are undefined, regular permissions are applied to offline client computers.

# To undefine offline permissions

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under Protocols, select Permissions.
When you select Permissions in the console tree, in the details pane you can view protocols for which you can set permissions. In the details pane you can also view the current state of offline permissions for each protocol in the Offline column.

4. In the details pane, right-click the protocol for which you want to undefine offline permissions, and then click **Undefine Offline**.

*You can undefine offline permissions set for several protocols at the same time. To do this, do the following:* 

- a) In the details pane, select several protocols by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Undefine Offline**.

The offline state of the permissions changes to "Not Configured."

#### **Removing Offline Permissions**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline permissions and enforce regular permissions on specific lower-level groups of client computers. To enforce regular permissions, you must remove offline permissions.

#### To remove offline permissions

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, select **Permissions**.

When you select Permissions in the console tree, in the details pane you can view protocols for which you can set permissions. In the details pane you can also view the current state of offline permissions for each protocol in the Offline column.

4. In the details pane, right-click the protocol for which you want to remove offline permissions, and then click **Remove Offline**.

You can remove offline permissions set for several protocols at the same time. To do this, do the following:

- a) In the details pane, select several protocols by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection and then click **Remove Offline**.

The offline state of the permissions changes to "Use Regular."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

#### Managing Offline Audit and Shadowing Rules for Protocols

For a detailed description of the Auditing & Shadowing feature for protocols, see "<u>Managing</u> <u>Audit and Shadowing Rules for Protocols</u>."

STATE	DESCRIPTION			
Not Configured	Indicates that audit and shadowing rules are not defined for a protocol. This is the default state.			
Configured	Indicates that audit and shadowing rules are defined for a protocol.			
No Audit	<ul> <li>Indicates one of the following:</li> <li>Audit rights are not set for all of the users and groups specified in audit and shadowing rules for a protocol.</li> <li>All users and groups specified in audit and shadowing rules for a protocol. are removed.</li> <li>The Everyone account has no Audit and Shadowing rights and is the only account specified in audit and shadowing rules for a protocol.</li> </ul>			
Use Regular	Indicates that the inheritance of offline audit and shadowing rules is blocked and regular audit and shadowing rules are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager. The enforcement of regular rules is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular rules lets you prevent offline rules inherited from a higher level from being applied to a specific group of client computers at a lower level. For more information on the enforcement of regular rules, see " <u>Removing Offline</u> Audit and Shadowing Rules."			

Offline audit and shadowing rules can have one of the following states:

Managing offline audit and shadowing rules involves the following tasks:

- Defining and editing offline audit and shadowing rules
- Undefining offline audit and shadowing rules
- Removing offline audit and shadowing rules

#### Defining and Editing Offline Audit and Shadowing Rules

#### To define and edit offline audit and shadowing rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under Protocols, select Auditing & Shadowing.

When you select Auditing & Shadowing in the console tree, in the details pane you can view protocols for which you can define audit and shadowing rules. In the details pane you can also view the current state of offline rules for each protocol in the Offline column.

- 4. In the details pane, do one of the following:
  - Right-click the protocol for which you want to define or edit rules, and then click Set Offline Auditing & Shadowing.
     OR -
  - Select the protocol for which you want to define or edit rules, and then click
     Set Offline Auditing & Shadowing 64 on the toolbar.

Auditing & Shadowing (Offline)		?
rotocol(s): FTP iomputer Name: Local Computer Audit Allowed Audit Denied		
Users	€ ♦	¢
Not Configured	12 * 2 * 4 * 6 * 8 * 10 * 12 * 2 * 4 * 6 * 8	= 10 = 12
	Al	
	Sunday	
Add Delete Set Default	Monday	
I Iser's Rinhts Allow	Tuesday	
Audt	Wednesday	
Connection	Thursday	
Outgoing Files	Friday	
Incoming Files	Saturday	
Outgoing Files	III - Audt Time III - Non-audt Time	
L]	OK Cancel	Apply

The Auditing & Shadowing (Offline) dialog box appears.

5. In the Auditing & Shadowing (Offline) dialog box, do the following:

TO DO THIS	FOLLOW THESE STEPS
To define the default audit	<ol> <li>In the upper-left area of the dialog box, specify which events are written to the Audit Log. Select the <b>Audit Allowed</b> check box to</li> </ol>

TO DO THIS	FOLLOW THESE STEPS
and shadowing rules	audit successful attempts to gain access to a protocol. Select the <b>Audit Denied</b> check box to audit unsuccessful attempts to gain access to a protocol.
	<ol> <li>In the upper-left pane of the dialog box, under Users, click Set Default.</li> </ol>
	The default audit and shadowing rules apply to the Users and Everyone groups. For information about which Audit and Shadowing rights are set for these groups by default, see " <u>Managing Audit and Shadowing Rules for Protocols</u> ."
To define audit and shadowing rules for an additional	<ol> <li>In the upper-left area of the dialog box, specify which events are written to the Audit Log. Select the <b>Audit Allowed</b> check box to audit successful attempts to gain access to a protocol. Select the <b>Audit Denied</b> check box to audit unsuccessful attempts to gain access to a protocol.</li> </ol>
user or group	2. In the upper-left pane of the dialog box, under <b>Users</b> , click <b>Add</b> .
	<ol> <li>In the Select Users or Groups dialog box appears.</li> <li>In the Select Users or Groups dialog box, in the Enter the object names to select box, type the name of the user or group, and then click OK.</li> </ol>
	The users and groups that you added are displayed under Users in the upper-left pane of the Auditing & Shadowing (Offline) dialog box.
	<ol> <li>In the upper-left pane of the Auditing &amp; Shadowing (Offline) dialog box, under Users, select the user or group.</li> </ol>
	5. You can select multiple users and/ or groups by holding down the SHIFT key or the CTRL key while clicking them.
	<ol> <li>In the lower-left pane of the Auditing &amp; Shadowing (Offline) dialog box, under User's Rights, select or clear the Allow check box next to the appropriate audit and shadowing rights.</li> </ol>
	Audit and Shadowing rights determine which user actions on protocols are logged to the Audit and/or Shadow Log. In the right pane of the Auditing & Shadowing (Offline) dialog box, you can specify days and hours (for example, from 7 AM to 5 PM Monday through Friday) when the selected user's actions on protocols will be logged to either the Audit or Shadow Log. Use the left mouse button to select days and hours when the selected user's actions on protocols will be logged. Use the right mouse button to mark days and hours when the selected user's actions on protocols will not be logged.
To change audit and	<ol> <li>In the upper-left pane of the dialog box, under Users, select the user or group.</li> </ol>
shadowing rules for an existing user or group	<ol> <li>In the lower-left pane of the dialog box, under User's Rights, select or clear the Allow check box next to the appropriate audit and shadowing rights.</li> </ol>
To remove an existing user or group and rules	<ul> <li>In the upper-left pane of the dialog box, under Users, select the user or group, and then click Delete or press the DELETE key.</li> <li>When you remove a user or group, any rules for that user or group will also be removed.</li> </ul>

6. Click **OK** or **Apply**.

#### **Undefining Offline Audit and Shadowing Rules**

You can return previously defined offline audit and shadowing rules to the unconfigured state. If offline rules are undefined, regular rules are applied to offline client computers.

#### To undefine offline audit and shadowing rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under Protocols, select Auditing & Shadowing.

When you select Auditing & Shadowing in the console tree, in the details pane you can view protocols for which you can define audit and shadowing rules. In the details pane you can also view the current state of offline rules for each protocol in the Offline column.

4. In the details pane, right-click the protocol for which you want to undefine offline audit and shadowing rules, and then click **Undefine Offline**.

You can undefine audit and shadowing rules defined for several protocols at the same time. To do this, do the following:

- a) In the details pane, select several protocols by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Undefine Offline**. The offline state of the audit and shadowing rules changes to "Not Configured."

#### **Removing Offline Audit and Shadowing Rules**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline audit and shadowing rules and enforce regular audit and shadowing rules on specific lower-level groups of client computers. To enforce regular audit and shadowing rules, you must remove offline audit and shadowing rules.

#### To remove offline audit and shadowing rules

1. If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, select **Auditing & Shadowing**.

When you select Auditing & Shadowing in the console tree, in the details pane you can view protocols for which you can define audit and shadowing rules. In the details pane you can also view the current state of offline rules for each protocol in the Offline column.

4. In the details pane, right-click the protocol for which you want to remove offline audit and shadowing rules, and then click **Remove Offline**.

You can remove audit and shadowing rules defined for several protocols at the same time. To do this, do the following:

- a) In the details pane, select several protocols by holding down the SHIFT key or the CTRL key while clicking them.
- b) Right-click the selection, and then click **Remove Offline**.

The offline state of the audit and shadowing rules changes to "Use Regular."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

#### **Managing Offline Protocols White List**

For a detailed description of the Protocols White List feature, see "<u>Managing Protocols White</u> <u>List (Regular Profile)</u>."

STATE	DESCRIPTION		
Not Configured	Indicates that the white list is not defined. The following message is displayed: "Offline Protocols White List is not configured." This is the default state.		
Configured	Indicates that the white list is defined.		
Use Regular	Indicates that the inheritance of the offline white list is blocked and the regular white list is enforced. The following message is displayed: "Offline Protocols White List is configured to use Regular Protocols White List." Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.		
	The enforcement of the regular white list is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of the regular white list lets you prevent the offline white list inherited from a higher level from being applied to a specific		

The offline Protocols White List can have one of the following states:

STATE	DESCRIPTION
	group of client computers at a lower level.
	For more information on the enforcement of the regular white list, see " <u>Removing</u> <u>Offline Protocols White List</u> ."

Managing the offline Protocols White List involves the following tasks:

- Defining the offline Protocols White List
- Editing the offline Protocols White List
- Copying rules of the offline Protocols White List
- Exporting and importing the offline Protocols White List
- Deleting rules of the offline Protocols White List
- Undefining the offline Protocols White List
- Removing the offline Protocols White List

#### Defining Offline Protocols White List

#### To define the offline Protocols White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click White List, and then click Manage Offline.
     OR -
  - Select White List, and then click Manage Offline is on the toolbar.

The Protocols White List (Offline) dialog box appears.

Protocols White List (Offlin	ne)			?
sers:	Rules:			
Users A	Description Protocol H	losts Ports	SSL	Extra param
Add Delete	Add Edit Delete			Load Save

4. In the left pane of the **Protocols White List (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

5. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups for which you want to define the Protocols White List, and then click **OK**.

The users and groups that you added are displayed under Users in the left pane of the Protocols White List (Offline) dialog box.

To delete a user or group, in the left pane of the **Protocols White List (Offline)** dialog box, under **Users**, select the user or group, and then click **Delete**.

6. In the left pane of the **Protocols White List (Offline)** dialog box, under **Users**, select the user or group.

You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

7. In the right pane of the **Protocols White List (Offline)** dialog box, under **Rules**, click **Add**.

📑 Add Rule	? 🛛
Protocol:	
Description:	OK Cancel

The Add Rule dialog box appears.

- 8. In the **Add Rule** dialog box, specify general and protocol-specific parameters for this rule. To specify general parameters, do the following:
  - To specify the protocol, in the **Protocol:** list, click the protocol of your choice.
  - To specify the rule name, in the **Description** box, type a name.

To specify protocol-specific parameters, do the following:

- To specify the hosts, in the **Hosts:** box, type host names or IP addresses separated by a comma or semicolon. For more information on how to specify hosts, see the <u>description of the Hosts parameter</u>.
- To specify the ports, in the **Ports:** box, type port numbers separated by a comma or semicolon. For more information on how to specify ports, see the <u>description of the Ports parameter</u>.
- To configure the SSL options, under **SSL**, click any of the following: **Allowed** (allows SSL connections), **Denied** (disallows SSL connections), or **Required** (requires that all connections use SSL).
- To specify the IM local sender ID(s), in the Local sender ID(s): box, type user identifiers separated by a comma or semicolon. For more information on how to specify user identifiers, see the <u>description of the Local sender ID(s)</u> <u>parameter</u>.
- To specify the IM remote recipient ID(s), in the Remote recipient ID(s): box, type user identifiers separated by a comma or semicolon. For more information on how to specify user identifiers, see the <u>description of the</u> <u>Remote recipient ID(s) parameter</u>.
- To specify the e-mail senders, in the Local sender Email(s): box, type sender addresses separated by a comma or semicolon. For more information on how to specify sender addresses, see the <u>description of the Local sender</u> <u>Email(s): parameter</u>.
- To specify the e-mail recipients, in the **Remote recipient Email(s):** box, type recipient addresses separated by a comma or semicolon. For more information on how to specify recipient addresses, see the <u>description of the Remote recipient Email(s): parameter</u>.
- To specify the social networking sites, under Social Networks:, select the appropriate check boxes. For more information, see the <u>description of the</u> <u>Social Networks: parameter</u>.
- To specify the Web-based e-mail services, under Web Mail Services:, select the appropriate check boxes. For more information, see the <u>description of the</u> <u>Web Mail Services: parameter</u>.
- 9. Click **OK**.

*The rule you created is displayed under Rules in the right pane of the Protocols White List (Offline) dialog box.* 

#### 10. Click **OK** or **Apply**.

The users or groups to which the white list rule applies are displayed under White List in the console tree.

When you select a user or group to which a white list rule applies in the console tree, in the details pane you can view detailed information regarding this rule. This information includes the following:

- **Protocol** The protocol the rule applies to.
- **Description** The name of the rule.
- **Hosts** Shows the allowed hosts for this rule.
- **Ports** Shows the allowed ports for this rule.
- **SSL** Shows the selected SSL option. Possible values: **Allowed** (allows SSL connections), **Denied** (disallows SSL connections), and **Required** (requires that all connections use SSL).

- **Extra parameters** Shows additional protocol-specific parameters specified for the rule. These parameters include: **From** (shows allowed sender identifiers for instant messaging and e-mail sender addresses for Webmail) and **To** (shows allowed recipient identifiers for instant messaging and e-mail recipient addresses for Webmail).
- **Profile** Possible values: **Regular** and **Offline**. **Regular** indicates that the rule applies to client computers that are working online. **Offline** indicates that the rule applies to computers that are working offline. You can define different online vs. offline Protocols White Lists for the same user or sets of users. For information about how to define the online Protocols White List, see "Managing Protocols White List."

#### **Editing Offline Protocols White List**

You can modify parameter values specified for an offline white list rule any time you want.

#### To edit an offline white list rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand Protocols.
- 3. Under **Protocols**, right-click **White List**, click **Manage Offline**, and then do the following:
  - a) In the left pane of the Protocols White List (Offline) dialog box, under Users, select the user or group for which you want to edit the rule.
     By selecting users or groups, you can view the white list rules applied to them under Rules in the right pane of the dialog box.
  - b) In the right pane of the Protocols White List (Offline) dialog box, under Rules, select the rule you want to edit, and then click Edit.
     OR -

Right-click the rule, and then click **Edit**.

- OR -

Under **Protocols**, expand **White List**, and then do the following:

a) Under **White List**, select the user or group for which you want to edit the rule.

By selecting users or groups, you can view the white list rules applied to them in the details pane.

b) In the details pane, right-click the rule you want to edit, and then click **Edit**.

- OR -

In the details pane, double-click the rule you want to edit.

The Edit Rule dialog box appears.

- 4. In the **Edit Rule** dialog box, modify the rule parameters as required to meet your needs.
- 5. Click **OK** to apply the changes.

#### **Copying Rules of Offline Protocols White List**

You can perform a cut-and-paste operation, a copy-and-paste operation or a drag-and-drop operation to reuse existing rules of the offline Protocols White List.

#### To copy an offline white list rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLoc**k.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click White List, and then click Manage Offline.
     OR -
  - Select White List, and then click Manage Offline is on the toolbar.

The Protocols White List (Offline) dialog box appears.

4. In the left pane of the **Protocols White List (Offline)** dialog box, under **Users**, select the user or group to which the rule that you want to copy is applied.

*By selecting users or groups, you can view the white list rules applied to them under Rules in the right pane of the dialog box.* 

5. In the right pane of the **Protocols White List Offline)** dialog box, under **Rules**, right-click the rule you want to copy, and then click **Copy** or **Cut**.

The rule you cut or copy is automatically copied to the Clipboard.

You can use the CTRL+C, CTRL+X and CTRL+V key combinations to copy, cut and paste the rule. When you use the CTRL+X key combination to cut the rule, the rule will be cut only after you paste it.

6. In the left pane of the **Protocols White List (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

7. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups to which you want to apply the copied rule, and then click **OK**.

The users and groups that you added are displayed under Users in the left pane of the Protocols White List (Offline) dialog box.

8. In the left pane of the **Protocols White List** (**Offline**)dialog box, under **Users**, select the users or groups to which you want to apply the copied rule.

You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

9. In the right pane of the **Protocols White List (Offline)** dialog box, right-click in the **Rules** pane and then click **Paste**.

The copied rule is displayed under Rules in the right pane of the Protocols White List dialog box.

10. Click **OK** or **Apply** to apply the copied rule.

#### **Exporting and Importing Offline Protocols White List**

You can export all your current rules of the offline Protocols White List to a .pwl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

#### To export the offline Protocols White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click White List, and then click Save Offline.
     OR -
  - Select White List, and then click Save Offline 
     OR -
  - Expand **White List**, right-click any user or group specified in the white list, and then click **Save Offline**.
    - OR -

- Expand White List, select any user or group specified in the white list. In the details pane, right-click the white list rule, and then click Save.
   OR –
- Expand White List, select any user or group specified in the white list, and then click Save Offline I on the toolbar.
   OR -
- Right-click White List, and then click Manage Offline. In the right pane of the Protocols White List (Offline) dialog box, under Rules, click Save.

The Save As dialog box appears.

- 4. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .pwl file.
- 5. In the **File name** box, type the file name you want.
- 6. Click **Save**.

When you export the offline Protocols White List, it is saved in a file with a .pwl extension.

#### To import the offline Protocols White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click White List, and then click Load Offline.
     OR -
  - Select White List, and then click Load Offline is on the toolbar.
     OR -
  - Expand White List, right-click any user or group specified in the white list, and then click Load Offline.
    - OR -
  - Expand White List, select any user or group specified in the white list. In the details pane, right-click the white list rule, and then click Load.
     OR -
  - Expand White List, select any user or group specified in the white list, and then click Load Offline 🛋 on the toolbar.

- OR-

• Right-click White List, and then click Manage Offline. In the right pane of the Protocols White List (Offline) dialog box, under Rules, click Load.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open.**

If the offline Protocols White List is already defined and you choose to import a new offline white list, the following message box is displayed.

DeviceL	ock 🛛 🛛
2	Do you want to overwrite existing records (Yes - Overwrite, No - Append)?
	Yes No Cancel

In the message box, click **Yes** to overwrite the existing offline white list. Click **No** to append a new offline white list to the existing offline white list.

#### **Deleting Rules of Offline Protocols White List**

You can delete individual rules of the offline Protocols White List when they are no longer required.

#### To delete an offline white list rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Expand **White List**, right-click the user or group to which the rule is applied, and then click **Delete user**.

When you delete a user or group, the rule associated with this user or group is automatically deleted.

- OR -

- Expand White List, and then select the user or group to which the rule is applied. In the details pane, right-click the rule associated with this user or group, and then click Delete.
   OR -
- Right-click White List, and then click Manage Offline. In the left pane of the Protocols White List (Offline) dialog box, under Users, select the user or group to which the rule is applied. In the right pane of the Protocols White List (Offline) dialog box, under Rules, select the rule, and then click Delete or right-click the rule, and then click Delete.

#### **Undefining Offline Protocols White List**

You can return the previously defined offline white list to the unconfigured state. If the offline white list is undefined, the regular white list is applied to offline client computers.

#### To undefine the offline Protocols White List

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand Protocols.
- 3. Under **Protocols**, right-click **White List**, and then click **Undefine Offline**.

The offline state of the white list changes to "Not Configured."

When you select **White List** in the console tree, in the details pane the following message is displayed: "Offline Protocols White List is not configured."

#### **Removing Offline Protocols White List**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of the higher-level offline white list and enforce the regular white list on specific lower-level groups of client computers. To enforce the regular Protocols White List, you must remove the offline Protocols White List.

#### To remove the offline Protocols White List

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.

b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, right-click **White List**, and then click **Remove Offline**.

The offline state of the white list changes to "Use Regular."

When you select **White List** in the console tree, in the details pane the following message is displayed: "Offline Protocols White List is configured to use Regular Protocols White List."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

#### **Managing Offline Content-Aware Rules for Protocols**

For a detailed description of the Content-Aware Rules feature for protocols, see "<u>Content-Aware Rules for Protocols (Regular Profile)</u>."

STATE	DESCRIPTION		
Not Configured	Indicates that Content-Aware Rules are not defined. The following message is displayed: "Offline Content-Aware Rules are not configured." This is the default state.		
Configured	Indicates that Content-Aware Rules are defined.		
Use Regular	Indicates that the inheritance of offline Content-Aware Rules is blocked and regular Content-Aware Rules are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.		
	The enforcement of regular Content-Aware Rules is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular Content-Aware Rules lets you prevent offline Content-Aware Rules inherited from a higher level from being applied to a specific group of client computers at a lower level.		
	For more information on the enforcement of regular Content-Aware Rules, see " <u>Removing Offline Content-Aware Rules.</u> "		

The offline Content-Aware Rules can have one of the following states:

Managing offline Content-Aware Rules involves the following tasks:

- Defining offline Content-Aware Rules
- Editing offline Content-Aware Rules
- Copying offline Content-Aware Rules
- Exporting and importing offline Content-Aware Rules

- Deleting offline Content-Aware Rules
- Undefining offline Content-Aware Rules
- Removing offline Content-Aware Rules

#### **Defining Offline Content-Aware Rules**

Content-Aware Rules are created based on either the built-in or custom content groups. For detailed information on these groups, see "<u>Configuring Content Detection Settings</u>."

#### To define an offline Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage Offline.
     OR -

The Content-Aware Rules (Offline) dialog box appears.

🗠 Content-Aware Rules (Offline)						22
Content Database						
Description				Туре		^
ABA Routing Number				Pattern (	buit-in)	
Acquisition				Keyword	s (built-in)	
Admission Discharge				Keyword	s (built-in)	
R Adult Keywords				Keyword	s (built-in)	
American Address				Keyword	s (built-in)	
American Name				Keyword	s (built-in)	
Archives				File Type	Detection (built-in)	
Audio, Video & Flash				File Type	Detection (built-in)	
R Bank ABA				Keyword	s (buit-in)	~
Add Test Group Duri	icate Add G	roup v View (	Group Delete Gro	show: All Th	pes	~
Users	Rules					
Users A	Description	Туре	Action(s)	Applies To	Protocol(s)	
	Palata	2.4	Ьġ			
Add Delete	Delete	Edit		ОК	Cancel A	eely

4. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

5. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups for which you want to define the rule, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules (Offline) dialog box.

To delete a user or group, in the lower-left pane of the **Content-Aware Rules** (Offline) dialog box, under **Users**, select the user or group, and then click **Delete** or press the DELETE key.

6. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the users or groups for which you want to define the rule.

*You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.* 

7. In the upper pane of the **Content-Aware Rules (Offline)** dialog box, under **Content Database**, select the desired content group, and then click **Add**.

**Note:** You can specify only one content group for a Content-Aware Rule.

The Add Rule dialog box appears.

Add Rule	2
Applies to Permissions Shadowing	
Protocol(s):	
Actions	
User's Rights	Allow Deny

8. In the **Add Rule** dialog box, in the **Description** box, type the name of the Content-Aware Rule.

By default, the Content-Aware Rule has the same name as the specified content group but you can enter a different name.

- 9. Under **Applies to**, specify the type of operation associated with the rule. The available options are:
  - **Permissions**: Specifies that the rule will apply to access control operations.
  - **Shadowing**: Specifies that the rule will apply to shadow copy operations.
  - **Permissions**, **Shadowing**: Specifies that the rule will apply to both access control and shadow copy operations.
- 10. Under **Protocol(s)**, select the appropriate protocol(s) you would like this rule to be applied to.

Content-Aware Rules can be applied to the following protocols: FTP, HTTP, ICQ/AOL Messenger, IRC, Jabber, Mail.ru Agent, SMTP, Social Networks, Web Mail, Windows Messenger, and Yahoo Messenger.

If you select several protocols that have different access rights, under Action(s), the dialog box displays only those access rights that are common to all selected protocols.

11. Under **Action(s)**, specify which user actions are allowed or disallowed on protocols and which user actions are logged to the Shadow Log.

For detailed information on user rights that can be specified in Content-Aware Rules, see "<u>Content-Aware Rules for Access Control Operations</u>" and "<u>Content-Aware Rules for Shadow Copy Operations</u>."

#### 12. Click **OK**.

The rule you created is displayed under Rules in the lower-right pane of the Content-Aware Rules (Offline) dialog box.

13. Click **OK** or **Apply** to apply the rule.

The users or groups to which the Content-Aware Rule applies are displayed under Content-Aware Rules in the console tree. When you select a user or group to which a Content-Aware Rule applies in the console tree, in the details pane you can view detailed information regarding this rule. This information includes the following:

- **Description** The name of the rule. By default, the rule has the same name as the specified content group.
- Type The type of the content analysis. Possible values: File Type Detection, Keywords, Pattern, Document Properties, and Complex. File Type Detection indicates that recognition and identification of files is based on their characteristic signatures. Keywords indicates that recognition and identification of data/files is based on the specified keywords or phrases.
   Pattern indicates that recognition and identification of data/files is based on the specified patterns of text described by Perl regular expressions.
   Document Properties indicates that recognition and identification of files is based on their properties. Complex indicates that recognition and identification of data/files is based on the specified content described by a Boolean expression.
- Action(s) Shows which user actions are allowed or disallowed on protocols and which user actions are logged to the Shadow Log.
- Applies To Possible values: Permissions, Shadowing, and Permissions, Shadowing. Permissions indicates that the rule applies to access control operations. Shadowing indicates that the rule applies to shadow copy operations. Permissions, Shadowing indicates that the rule applies to both access control and shadow copy operations.
- **Protocol(s)** The protocol(s) to which the rule applies.
- **Profile** Possible values: **Regular** and **Offline**. **Regular** indicates that the rule applies to client computers that are working online. **Offline** indicates that the rule applies to computers that are working offline. You can define different online vs. offline Content-Aware Rules for the same user or sets of users. For information about how to define online Content-Aware Rules for protocols, see "Managing Content-Aware Rules."

#### **Editing Offline Content-Aware Rules**

You can modify the Content-Aware Rule properties such as Description, Applies To, Protocol(s), Actions.

#### To edit an offline Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, right-click **Content-Aware Rules**, click **Manage Offline**, and then do the following:
  - a) In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the user or group for which you want to edit the rule. *By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.*
  - b) In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, under **Rules**, select the rule you want to edit, and then click **Edit**.

- OR -

Under **Protocols**, expand **Content-Aware Rules**, and then do the following:

a) Under **Content-Aware Rules**, select the user or group for which you want to edit the rule.

By selecting users or groups, you can view the Content-Aware Rules applied to them in the details pane.

b) In the details pane, right-click the rule you want to edit, and then click Edit.
 - OR -

In the details pane, double-click the rule you want to edit.

The Edit Rule dialog box appears.

- 4. In the **Edit Rule** dialog box, modify the rule properties as required to meet your needs.
- 5. Click **OK** to apply the changes.

#### **Copying Offline Content-Aware Rules**

You can perform a cut-and-paste operation, a copy-and-paste operation or a drag-and-drop operation to reuse existing offline Content-Aware Rules.

#### To copy an offline Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.

- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Manage Offline.
     OR -
  - Select Content-Aware Rules, and then click Manage Offline 
     on the toolbar.

The Content-Aware Rules (Offline) dialog box appears.

4. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the user or group to which the rule that you want to copy is applied.

*By selecting users or groups, you can view the Content-Aware Rules applied to them under Rules in the lower-right pane of the dialog box.* 

5. In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, under **Rules**, right-click the rule you want to copy, and then click **Copy** or **Cut**.

The rule you cut or copy is automatically copied to the Clipboard.

You can use the CTRL+C, CTRL+X and CTRL+V key combinations to copy, cut and paste the rule. When you use the CTRL+X key combination to cut the rule, the rule will be cut only after you paste it.

To perform a drag-and-drop operation, select the rule and move it to the user or group to which you want to apply the copied rule.

6. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, click **Add**.

The Select Users or Groups dialog box appears.

7. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type the names of the users or groups to which you want to apply the copied rule, and then click **OK**.

The users and groups that you added are displayed under Users in the lower-left pane of the Content-Aware Rules (Offline) dialog box.

8. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the users or groups to which you want to apply the copied rule.

You can select multiple users or groups by holding down the SHIFT key or the CTRL key while clicking them.

9. In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, rightclick in the **Rules** pane and then click **Paste**.

The copied rule is displayed under Rules in the lower-right pane of the Content-Aware Rules (Offline) dialog box.

10. Click **OK** or **Apply** to apply the copied rule.

#### **Exporting and Importing Offline Content-Aware Rules**

You can export all your current offline Content-Aware Rules to a .cwl file that you can import and use on another computer. Exporting and importing can also be used as a form of backup.

#### **To export offline Content-Aware Rules**

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Right-click Content-Aware Rules, and then click Save Offline.
     OR -
  - Select Content-Aware Rules, and then click Save Offline 
     on the toolbar.
    - OR -
  - Expand Content-Aware Rules, right-click any user or group to which the rule is applied, and then click Save Offline.
     OR -
  - Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Save**.
    - OR -
  - Expand Content-Aware Rules, select any user or group to which the rule is applied, and then click Save Offline Source on the toolbar.
     OR -
  - Right-click Content-Aware Rules, and then click Manage Offline. In the lower-right pane of the Content-Aware Rules (Offline) dialog box, under Rules, click Save.

The Save As dialog box appears.

- 4. In the **Save As** dialog box, in the **Save in** box, browse to the location where you want to save the .cwl file.
- 5. In the **File name** box, type the file name you want.
- 6. Click Save.

When you export rules, they are saved in a file with a .cwl extension.

#### **To import offline Content-Aware Rules**

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.
- If you use DeviceLock Group Policy Manager, do the following:
  - a) Open Group Policy Object Editor.
  - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**., do one of the following:
  - Right-click Content-Aware Rules, and then click Load Offline.
     OR -
  - Select Content-Aware Rules, and then click Load Offline is on the toolbar.
    - OR -
  - Expand Content-Aware Rules, right-click any user or group to which the rule is applied, and then click Load Offline.
     OR -
  - Expand **Content-Aware Rules**, and then select any user or group to which the rule is applied. In the details pane, right-click the rule, and then click **Load**.
    - OR -
  - Expand Content-Aware Rules, select any user or group to which the rule is applied, and then click Load Offline and the toolbar.
     OR -
  - Right-click **Content-Aware Rules**, and then click **Manage Offline**. In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, under **Rules**, click **Load**.

The Open dialog box appears.

- 4. In the **Open** dialog box, in the **Look in** list, click the location that contains the file you want to import.
- 5. In the folder list, locate and open the folder that contains the file.
- 6. Click the file, and then click **Open**.

You can import only one .cwl file at a time.

#### **Deleting Offline Content-Aware Rules**

You can delete individual offline Content-Aware Rules when they are no longer required.

#### To delete an offline Content-Aware Rule

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Expand Content-Aware Rules, right-click the user or group to which the rule is applied, and then click Delete user.
     When you delete a user or group, the rule associated with this user or group is automatically deleted.

- OR -

• Expand **Content-Aware Rules**, and then select the user or group to which the rule is applied. In the details pane, right-click the rule associated with this user or group, and then click **Delete**.

- OR -

• Right-click **Content-Aware Rules**, and then click **Manage Offline**. In the lower-left pane of the **Content-Aware Rules (Offline)** dialog box, under **Users**, select the user or group to which the rule is applied. In the lower-right pane of the **Content-Aware Rules (Offline)** dialog box, under **Rules**, select the rule, and then click **Delete**.

You can select multiple rules that you want to delete by holding down the SHIFT key or the CTRL key while clicking them.

#### **Undefining Offline Content-Aware Rules**

You can return the previously defined offline Content-Aware Rules to the unconfigured state. If offline rules are undefined, regular rules are applied to offline client computers.

#### To undefine offline Content-Aware Rules

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Service Settings Editor, do the following:

- a) Open DeviceLock Service Settings Editor.
- b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under **Protocols**, right-click **Content-Aware Rules**, and then click **Undefine Offline**.

The offline state of Content-Aware Rules changes to "Not Configured."

When you select **Content-Aware Rules** in the console tree, in the details pane the following message is displayed: "Offline Content-Aware Rules are not configured."

#### **Removing Offline Content-Aware Rules**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline Content-Aware Rules and enforce regular Content-Aware Rules on specific lower-level groups of client computers. To enforce regular Content-Aware Rules, you must remove offline Content-Aware Rules.

#### To remove offline Content-Aware Rules

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand Protocols.
- 3. Under **Protocols**, right-click **Content-Aware Rules**, and then click **Remove Offline**.

The offline state of Content-Aware Rules changes to "Use Regular."

When you select **Content-Aware Rules** in the console tree, in the details pane the following message is displayed: "Offline Content-Aware Rules are configured to use Regular Content-Aware Rules."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

#### **Managing Offline Security Settings for Protocols**

For a detailed description of the Security Settings feature for protocols, see "<u>Managing</u> <u>Security Settings for Protocols</u>."

Offline Security Settings can have one of the following states:

STATE	DESCRIPTION
Not Configured	Indicates that Security Settings are not defined for protocols. This is the default state.
Enabled	Indicates that Security Settings are enabled for protocols.
Disabled	Indicates that Security Settings are disabled for protocols.
Use Regular	Indicates that the inheritance of offline Security Settings is blocked and regular Security Settings are enforced. Offline DeviceLock settings can have this state only in DeviceLock Service Settings Editor or DeviceLock Group Policy Manager.
	The enforcement of regular Security Settings is useful if you use Group Policy or DeviceLock Service Settings files (.dls) to deploy DeviceLock policies throughout your network. The enforcement of regular Security Settings lets you prevent offline Security Settings inherited from a higher level from being applied to a specific group of client computers at a lower level.
	For more information on the enforcement of regular Security Settings, see " <u>Removing Offline Security Settings</u> ."

Managing offline Security Settings involves the following tasks:

- Defining and changing offline Security Settings
- Undefining offline Security Settings
- Removing offline Security Settings

#### **Defining and Changing Offline Security Settings**

#### To define and change offline Security Settings

- 1. If you use DeviceLock Management Console, do the following:
  - a) Open DeviceLock Management Console and connect it to the computer running DeviceLock Service.
  - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Service Settings Editor, do the following:
    - a) Open DeviceLock Service Settings Editor.
    - b) In the console tree, expand **DeviceLock Service**.
  - If you use DeviceLock Group Policy Manager, do the following:
    - a) Open Group Policy Object Editor.
    - b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.

- 2. Expand **Protocols**.
- 3. Under **Protocols**, do one of the following:
  - Select Security Settings. In the details pane, right-click the Security Setting, and then click Enable Offline or Disable Offline.
     When you select Security Settings in the console tree, they are displayed in the details pane.

- OR-

• Right-click **Security Settings**, and then click **Manage Offline**. In the **Security Settings (Offline)** dialog box that opens, select or clear the appropriate check box, and then click **OK**.

To open the Security Settings (Offline) dialog box, you can also select Security Settings, and then click Manage Offline is on the toolbar.

**Note:** All check boxes in the **Security Settings (Offline)** dialog box have three states: selected, cleared, and indeterminate that correspond to the Enabled, Disabled, and Not Configured states of Security Settings.

*The Security Setting changes its offline state from "Not Configured" to "Enabled" or "Disabled."* 

#### **Undefining Offline Security Settings**

You can return the previously defined offline Security Settings to the unconfigured state. If offline Security Settings are undefined, regular Security Settings are applied to offline client computers.

#### To undefine offline Security Settings

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, right-click **DeviceLock Settings** or **DeviceLock Service**, and then click **Load Service Settings** to open the XML file with defined offline DeviceLock policies.
  - c) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand Protocols.
- 3. Under **Protocols**, do one of the following:
  - Select **Security Settings**. In the details pane, right-click the Security Setting, and then click **Undefine**.

When you select Security Settings in the console tree, they are displayed in the details pane.

- OR –

• Right-click **Security Settings**, and then click **Manage Offline**. In the **Security Settings (Offline)** dialog box that opens, return the appropriate check box to the indeterminate state, and then click **OK**.

To open the Security Settings (Offline) dialog box, you can also select Security Settings, and then click Manage Offline **1** on the toolbar.

**Note:** All check boxes in the **Security Settings (Offline)** dialog box have three states: selected, cleared, and indeterminate that correspond to the Enabled, Disabled, and Not Configured states of Security Settings.

The Security Setting changes its offline state to "Not Configured."

#### **Removing Offline Security Settings**

If you deploy DeviceLock policies using Group Policy or DeviceLock Service Settings files (.dls), DeviceLock provides you with the ability to block the inheritance of higher-level offline Security Settings and enforce regular Security Settings on specific lower-level groups of client computers. To enforce regular Security Settings, you must remove offline Security Settings.

#### **To remove offline Security Settings**

- 1. If you use DeviceLock Service Settings Editor, do the following:
  - a) Open DeviceLock Service Settings Editor.
  - b) In the console tree, expand **DeviceLock Service**.

If you use DeviceLock Group Policy Manager, do the following:

- a) Open Group Policy Object Editor.
- b) In the console tree, expand **Computer Configuration**, and then expand **DeviceLock**.
- 2. Expand **Protocols**.
- 3. Under Protocols, select Security Settings.

When you select Security Settings in the console tree, they are displayed in the details pane.

4. In the details pane, right-click the Security Setting, and then click **Remove Offline**.

The Security Setting changes its offline state to "Use Regular."

*The "Use Regular" state of DeviceLock settings is displayed as "Not Configured" in DeviceLock Management Console.* 

## **Temporary White List**

The DeviceLock Temporary White List function enables the granting of temporary access to USB devices when there is no network connection. Administrators provide users with special access codes over the phone that temporarily unlock access to requested devices. The following diagram illustrates the process of granting temporary access to USB devices.



A Temporary White List works like a <u>device white list</u>, with the distinction that a network connection is not required to add devices and grant access to them.

**Note:** Using Temporary White List it is possible to grant access to USB devices that were blocked on both levels: the USB port level and the type level. If some white listed device (for example, USB Flash Drive) belongs to both levels: USB and type (Removable), the permissions (if any) for the type level are ignored as well as for the USB level.

Creating and activating a Temporary White List is a matter of following these step-by-step instructions:

- The administrator generates a cryptographic certificate (DeviceLock Certificate) using the <u>Certificate Generation Tool</u>. A DeviceLock Certificate consists of two keys: private and public.
- 2. The administrator deploys the DeviceLock Certificate (the public key) to a user's computer. This enables the Temporary White List on the user's computer.

- 3. When a user needs to access some USB device, he/she runs the <u>Temporary White</u> <u>List Authorization Tool</u> from the Windows Control Panel. Then the user selects the particular device from a list and a textual-numeric code (**Device Code**) is generated. The user can then provide this code to the DeviceLock Administrator over the phone or via an Internet chat session.
- 4. The administrator then runs the <u>DeviceLock Signing Tool</u>, loads the corresponding DeviceLock Certificate (the private key), enters the **Device Code**, selects an appropriate temporary access period (5, 15, etc. minutes, until the device is unplugged or until the user is logged off), generates an **Unlock Code**, and relays this **Unlock Code** to the user.
- 5. Upon receipt of the **Unlock Code**, the user enters it into <u>Temporary White List</u> <u>Authorization Tool</u>. Access to the requested device is then granted for the specified period.

### **Temporary White List Authorization Tool**

The Temporary White List Authorization Tool is a part of the Windows Control Panel applet that users should use to obtain temporary access to devices.

To run the Temporary White List Authorization Tool, the user should run the **DeviceLock** applet from the Control Panel and select the **Temporary White List Authorization Tool** option.



**Note:** On Windows XP and later, the user must switch the Control Panel to Classic View in order to view all available applets.



There are five simple steps for the user to request and obtain temporary access to a device:

- 1. Plug the needed device into the USB port.
- 2. Select the device from the list of all available USB devices.

<b>i</b>	DeviceLock Temporary White List Authorization Tool 🛛 🔹 💽 🔯	
	Select a device you want to obtain access to: USB Root Hub USB Mass Storage Device USB DISK 12X USB Device Generic volume (F:)	
-	< Back Next > Cancel	ļ

 Contact an Administrator and tell him/her the name of the certificate and the Device Code. Please note that the Device Code is only valid within 24 hours of the time it was generated by the applet.

🖹 DeviceLock Temporary White List Authorization Tool 🛛 🔹 💽
Call the Administrator and quote Device Code and Certificate Name displayed below: Certificate Name: DeviceLock Certificate [05/11/2006 01:28:52 PM] Device Code: B3MMH-24HXG-X4K3-NE5R-FK4T-GBFQ Enter Unlock Code the Administrator tells you in the fields below: 7M0LV - GNV21 - EU0ND - JTIPD - RBMGH - B723R - TBFJL Reinitialize the device before granting access
< Back Finish Cancel

4. Enter an **Unlock Code** received from the Administrator.

If it is necessary to force the requested device to reinitialize (replug) before allowing access to it, select the **Reinitialize device before granting access** check box.

Some USB devices (like the mouse) will not work without being reinitialized, so it is recommended to keep this check box selected for non-storage devices.

It is recommended to keep the **Reinitialize device before granting access** check box unselected for storage devices (such as flash drives, CD/DVD-ROMs, external hard drives and so on).

Some USB devices cannot be reinitialized from DeviceLock Service. It means that their drivers do not support the software replug. If such a device was white listed but does not work, the user should remove it from the port and then insert it back manually to restart the device's driver.

5. Press the **Finish** button.

If the **Unlock Code** is valid, then access to the device will be provided in several seconds.

DeviceLock Temporary White List Authorization Tool 🛛 🔀
The device has been successfully unlocked for 1 day.
OK

All successful attempts to add devices to a Temporary White List are logged, if logging of changes is enabled in <u>Service Options</u>.

## Appendix

### **Permissions and Audit Examples for Devices**

Using the following examples you can better understand how to properly define permissions, audit and shadowing rules in DeviceLock.

All examples assume that you are using DeviceLock Management Console (the MMC snapin) and it is already connected to the computer where DeviceLock Service is running. For more information on how to use DeviceLock Management Console, see "<u>DeviceLock</u> <u>Management Console</u>."

#### **Permissions Examples**

#### For all users all USB devices are denied except the mouse and keyboard:

1. Select the **USB port** record from the list of device types under **Permissions**, and then select **Set Permissions** from the context menu available by a right mouse click.

SeviceLock Management Console			
File Action View Help File Action View Help DeviceLock DeviceLock Service Service Options Devices Permissions Gor Auditing & Shadowing USB Devices White List Security Settings Audit Log Viewer Shadow Log Viewer	Name / Bluetooth DVD/CD-ROM FireWire port Fioppy Hard disk Infrared port Palm Palm Parallel port Printer		
Enterprise Server	Removable  Serial port  Tape  USB port  WIFi  Windows Mc	Set Permissions Flush Buffers Help	_
Manages permissions for selected device	(5)		

 Click the Add button in the Permissions dialog box, add the Everyone user (type the name or browse for all available names and select the needed one), click OK to close the Select Users or Groups dialog box, select the Everyone record and disable all rights in the User's Rights list.

🗟 Permissions	2
Devices Type(s): US8 port Computer Name: Local Computer	
Users	C 🔶 C
1 Everyone	12 * 2 * 4 * 6 * 8 * 10 * 12 * 2 * 4 * 6 * 8 * 10 * 12
	Al
	Sunday
Add Delete Set Default	Monday
User's Rights Allow	Tuesday
B Generic Read	Wednesday
Write	Thursday
Eject	Friday
	Saturday
	Allowed Time     - Denied Time
	Security Settings USB White List
	OK Cancel Apply

3. Click the **Security Settings** button in the **Permissions** dialog box, and then clear the **Access control for USB HID (mouse, keyboard, etc.)** check box.

🗟 Security Settings 📀 🔀
Access control for USB HID (mouse, keyboard, etc.) Access control for USB printers Access control for USB scanners and still image devices Access control for USB Bluetooth adapters Access control for USB storage devices Access control for USB and FireWire network cards
OK Cancel

 Click OK to close the Security Settings dialog box, click OK to apply changes and close the Permissions dialog box, and then click Yes to confirm that you really want to deny all users access to the USB port.

# For all users all USB devices are denied except the mouse and keyboard but members of the Administrators group can use all USB devices:

 Select the USB port record from the list of device types under Permissions, and then select Set Permissions from the context menu available by a right mouse click.  Click the Add button in the Permissions dialog box, add the Administrators group (type the name or browse for all available names and select the needed one), click OK to close the Select Users or Groups dialog box, select the Administrators record and enable all rights in the User's Rights list.

😤 Permissions	2	×
Devices Type(s): USB port Computer Name: Local Computer		
Users	j 🤅 🤪 🤅	
Administrators	12 • 2 • 4 • 6 • 8 • 10 • 12 • 2 • 4 • 6 • 8 • 10 • 12	
	Al	
	Sunday	
Add Dates Set Defait	Monday Monday	
Nos Desce Soc Descur	Tuesday	
Generic	Wednesday	
Write V	Thursday	
Eject 🗹	Friday	
	Saturday	
	Allowed Time      - Denied Time     Security Settings     USB White List	
	OK Cancel Apply	

3. Click the **Security Settings** button in the **Permissions** dialog box, and then clear the **Access control for USB HID (mouse, keyboard, etc.)** check box.



4. Click **OK** to close the **Security Settings** dialog box, and then click **OK** to apply changes and close the **Permissions** dialog box.
## For all users all storage devices except fixed hard drives are denied but all nonstorage USB devices are allowed:

 Select the USB port record from the list of device types under Permissions, and then select Set Permissions from the context menu available by a right mouse click.



 Click the Add button in the Permissions dialog box, add the Everyone user (type the name or browse for all available names and select the needed one), click OK to close the Select Users or Groups dialog box, select the Everyone record and enable all rights in the User's Rights list.



- 3. Click **OK** to apply changes and close the **Permissions** dialog box.
- 4. Select **DVD/CD-ROM**, **Floppy** and **Removable** records from the list of device types under **Permissions**, and then select **Set Permissions** from the context menu available by a right mouse click.

🖆 DeviceLock Management			
File Help File Help	Name / Bluetooth DVD/CD-ROM FireWire port Fioppy Hard disk Infrared port Parallel port Removable Serial port	Set Perm Flush Buff Help	nissions
Shadow Log Viewer     DeviceLock Enterprise Server	Tape		

5. Click the Add button in the Permissions dialog box, add the Everyone user (type the name or browse for all available names and select the needed one), click OK to close the Select Users or Groups dialog box, select the Everyone record and disable all rights in the User's Rights list.

😤 Permissions	
Devices Type(s): Floppy, Removable, DVD/CD-ROM Computer Name: Local Computer	
Users	C 🔶 C
22 Everyone	12 * 2 * 4 * 6 * 8 * 10 * 12 * 2 * 4 * 6 * 8 * 10 * 12
	AL
	Sunday
Add Delete Set Default	Monday
User's Rights Allow	Tuesday
Generic     Read	Wednesday
Write	Thursday
cjox 🗋	Friday
	Saturday
	Alowed Time     Derived Time
	Security Settings Media White List
	OK Cancel Apply

6. Click **OK** to apply changes and close the **Permissions** dialog box, and then click **Yes** to confirm that you really want to deny access to these devices for all users.

## For all users all USB devices are denied except the mouse and keyboard but members of the Administrators group can use an authorized model of USB storage devices:

- Select the USB port record from the list of device types under Permissions, and then select Set Permissions from the context menu available by a right mouse click.
- Click the Add button in the Permissions dialog box and add the Everyone user (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, select the Everyone record and disable all rights in the User's Rights list.
- 3. Click the **Security Settings** button in the **Permissions** dialog box, and then clear the **Access control for USB HID (mouse, keyboard, etc.)** check box.



4. Click **OK** to close the **Security Settings** dialog box, and then click the **USB White List** button in the **Permissions** dialog box.

State Contract State Contract State				? 🛛
USB Devices Database				
Description	DeviceID	Туре		
Lexar Flash Drive	USBWID_0D7D&PID	140 Unique Device		
Mini Flash	USB\VID_090A&PID_	1001 Device Model		
Add USB Devices Database			Show	All Tupes
USB Devices White List				
Users	Devices			
Users	Description	DeviceID	Reinitialize	Туре
APVIRT Administrators	😪 Mini Flash	USB\VID_090A&PID_1001		Device Model
Add Delete	Delete Edi		Lo	ad Save
			OK Car	cel Apply

- 5. Click the **Add** button below the **Users** list, add the **Administrators** group (type the name or browse for all available names and select the needed one), click **OK** to close the **Select Users or Groups** dialog box, and then select the **Administrators** record.
- 6. Select the device model's record in the **USB Devices Database** list, and then click the **Add** button below this list.

If you do not have devices in the **USB Devices Database** list, click the **USB Devices Database** button below this list, and then add devices as described in the "<u>USB Devices Database</u>" section of this manual. When you finished adding devices to the database, click **OK** to save this database and close the **USB Devices Database** dialog box. 7. Click **OK** to apply the white list settings and close the **USB Devices White List** dialog box, click **OK** to apply changes and close the **Permissions** dialog box, and then click **Yes** to confirm that you really want to deny all users access to the USB port.

### For all users all USB devices are denied except the mouse and keyboard but members of the Administrators group can use an authorized unique USB storage device:

- 1. Select the **USB port** record from the list of device types under **Permissions**, and then select **Set Permissions** from the context menu available by a right mouse click.
- Click the Add button in the Permissions dialog box and add the Everyone user (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, select the Everyone record and disable all rights in the User's Rights list.
- 3. Click the **Security Settings** button in the **Permissions** dialog box, and then clear the **Access control for USB HID (mouse, keyboard, etc.)** check box.



4. Click **OK** to close the **Security Settings** dialog box, and then click the **USB White List** button in the **Permissions** dialog box.

So Demosi Dalabase					
Description	DeviceID		Туре		
Lexar Flash Drive	USB\VID_0D7D	&PID_1400\073C1B300351	Unique Device		
🐨 Mini Flash	US8WID_090A8	PID_1001	Device Model		
Add USB Devices Data	abase			Show:	All Types
SB Devices White List Users	Devices				
Users	Description	DeviceID		Reinitialize	Type
Administrators	Lexar Flash	Drive USB\VID_0D7D&PID	_1400\073C1B300351		Unique Device

- Click the Add button below the Users list and add the Administrators group (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, and then select the Administrators record.
- 6. Select the unique device's record in the **USB Devices Database** list, and then click the **Add** button below this list.

If you do not have devices in the **USB Devices Database** list, click the **USB Devices Database** button below this list, and then add devices as described in the "<u>USB Devices Database</u>" section of this manual. When you finish adding devices to the database, click **OK** to save this database and close the **USB Devices Database** dialog box.

7. Click **OK** to apply the white list settings and close the **USB Devices White List** dialog box, click **OK** to apply changes and close the **Permissions** dialog box, and then click **Yes** to confirm that you really want to deny all users access to the USB port.

#### For all users all CD and DVD drives are set to the read-only mode but members of the Administrators group can burn (write) CD and DVD disks:

 Select the DVD/CD-ROM record from the list of device types under Permissions, and then select Set Permissions from the context menu available by a right mouse click.

File Action View Help - → 🗈 📧 😼 😰 🐍		
DeviceLock	Name 🛆	
DeviceLock Service	🛞 Bluetooth	
Service Options     Devices     Service Permissions	SireWire port	Set Permissions Flush Buffers
Auditing & Shadowing     Auditing & Shadowing     USB Devices White List     Security Settings     Audit Log Viewer     Shadow Log Viewer     DeviceLock Enterprise Server	Hard disk Infrared port Palm Parallel port Printer Removable Serial port Tape USB port Y WiFi Windows Mobile	Help

- Click the Add button in the Permissions dialog box and add the Administrators group (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, select the Administrators record and enable all rights in the User's Rights list.
- Click the Add button in the Permissions dialog box and add the Everyone user (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box. Select the Everyone record and disable the Write right in the User's Rights list.

💪 Permissions	2
Devices Type(s): DVD/CD-ROM Computer Name: Local Computer	
Users	€ 👙 €
2 Everyone	12 • 2 • 4 • 6 • 8 • 10 • 12 • 2 • 4 • 6 • 8 • 10 • 12
2 Administrators	Al
	Sunday
Add Delete Set Default	Monday
User's Rights Allow	Tuesday
B Generic	Wednesday
Write	Thursday
	Friday
	Saturday
	Security Settings Media White List
	OK Cancel Apply

4. Click **OK** to apply changes and close the **Permissions** dialog box.

# For all users all CD and DVD drives are denied but members of the Administrators group can read a certain disk:

- Select the DVD/CD-ROM record from the list of device types under Permissions, and then select Set Permissions from the context menu available by a right mouse click.
- Click the Add button in the Permissions dialog box and add the Everyone user (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, select the Everyone record and disable all rights in the User's Rights list.
- 3. Click the **Media White List** button in the **Permissions** dialog box.

🗟 Media White List					×
Media Database					
Description	MedialD		Туре		
S MSDA35	84BC7078092681DC095D6F	F344E68422D	DVD/CD-ROM		
SOLENTSEL	42F99FABE1717CB7C39D6	EZ3C442A7A9	DVD/CD-ROM		
Add Media Database					
Media White List	Media				1
Heart	Description	MerialD		Tune	
XPVIRT\Administrators	SQLENTSEL	42F99FABE1717CB70	39D6E23C442A7A9	DVD/CD-ROM	
Add Delete	Delete Edit			Load Save	
			OK	Cancel Apply	

- 4. Click the Add button below the Users list and add the Administrators group (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, and then select the Administrators record.
- 5. Select the media's record in the **Media Database** list, and then click the **Add** button below this list.

If you do not have records in the **Media Database** list, click the **Media Database** button below this list, and then authorize a media as described in the "<u>Media</u> <u>Database</u>" section of this manual. When you finish authorizing a media, click **OK** to save the database and close the **Media Database** dialog box.

 Click OK to apply the white list settings and close the Media White List dialog box. Click OK to apply changes and close the Permissions dialog box. Then click Yes to confirm that you really want to deny access to CD/DVD drives for all users.

# **Audit & Shadowing Rules Examples**

Log insert, remove and access actions for USB devices for all users:

 Select the USB port record from the list of device types under Auditing & Shadowing, and then select Set Auditing & Shadowing from the context menu available by a right mouse click.



 Click the Add button in the Audit dialog box and add the Everyone user (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, select the Everyone record and enable Read and Write audit rights in the User's Rights list.

Auditing & Shadowing														?
Devices Type(s): USB port Computer Name: Local Computer Audit Allowed	ed													
Users			E					٠						E
Everyone		1	12 • 2	• 4	• 6	• 8	• 10	12	2 .	4	• 6	• 8	• 10 •	12
		All												
		Sunday										i i		
Add	Delete Set Default	Monday			$^{++}$	Ħ	Ħ			T	Ħ	Ħ	Ħ	
User's Rights	Allow	Tuesday					Π				Π	Π		
Audt		Wednesday			T		Π			T	Π	П		
Write		Thursday			Т	П				T	Π	П		
112200		Friday			T	П					Π	П		
		Saturday				П					Π	Π		
				•	l- Audi	t Time	0.	Non-4	sudit T	ime				
							C	ОК		0	ancel		Ap	ply

3. Select the **Audit Allowed** and **Audit Denied** check box at the top of the **Audit** dialog box, and then click **OK** to apply changes and close the **Auditing & Shadowing** dialog box.

# *Log only files and folders names related to denied write actions for removable storage devices for members of the Users group:*

1. Select the **Removable** record from the list of device types under **Auditing & Shadowing**, and then select **Set Auditing & Shadowing** from the context menu available by a right mouse click.

🖆 DeviceLock Management		
File Help		
Smartline DeviceLock Content Service Service Options Service Options Shadowing Shadowi	Name / Parallel port Parallel port Removable Serial port USB port WiFi	Set Auditing & Shadowing Flush Buffers Help
Manages auditing and shadowing settings fo	r selected device(:	

 Click the Add button in the Audit dialog box and add the Users group (type the name or browse for all available names and select the needed one). Click OK to close the Select Users or Groups dialog box, select the Users record and enable only the Write audit right in the User's Rights list.



3. Select only the **Audit Denied** check box at the top of the **Audit** dialog, and then click **OK** to apply changes and close the **Auditing & Shadowing** dialog box.

#### Shadow all data writing to removable storage devices and floppies for all users:

- Select Floppy and Removable records from the list of device types under Auditing & Shadowing, and then select Set Auditing & Shadowing from the context menu available by a right mouse click.
- Click the Add button in the Audit dialog box and add the Everyone user. Click OK to close the Select Users or Groups dialog box and select the Everyone record. Disable all audit rights and enable only the Write shadowing right in the User's Rights list.

Auditing & Shadowing														2	
svices Type(s): Floppy, Removable omputer Name: Local Computer Audit Allowed Audit Denied															
Users			E .	2.	4 • •		• 10	• 12			4 .	6	• 10	6	2
Electeritorie		Al							T					T	
		Sunday													
Add Dek	te Set Default	Monday		Ħ				Ħ	T		Ħ			T	
User's Rights	Allow	luesday		Ħ				Π	T		Ħ			T	
Audit	W	ednesday		Π											
Write	Т	hursday		Π											
Shadowing		Friday		Π											
11160	s	iaturday		П											
					- Au	dit Tim	e C	] - Nor	1-800	lit Tim	ю				
							C	CR	(		Can	cel		Apply	,

3. Click **OK** to apply changes and close the **Auditing & Shadowing** dialog box.

# **Permissions Examples for Protocols**

# For all users all Webmail services are denied, but members of the Administrators group can access Gmail:

- 1. In the console tree, expand **DeviceLock Service**, and then expand **Protocols**.
- 2. Under **Protocols**, select **Permissions**.
- 3. In the details pane, right-click **Web Mail**, and then click **Set Permissions**.
- 4. In the **Permissions** dialog box, do the following:
  - a) Under Users, click Add. In the Select Users or Groups dialog box, in the Enter the object names to select box, type Everyone, and then click OK.
  - b) Under **Users**, select **Everyone**.
  - c) Under **User's Rights**, clear all check boxes to disable all rights.

Users			8		 	 	 		 		 
Treilioue			12 *	2	 - 0	 -	 12 .		 	11	 
		All									
		Sunday									
	- Cabbilit	Monday									
Add Delet	e Sec Deraut	Tuesday									
Generic	AllOW	Wednesday									
Send/Receive Data Outgoing Messages		Thursday	1								
Outgoing Files SSL		Friday									
Send/Receive Data Outgoing Messages Outgoing Files		Saturday									
	_				 			1.95.00			

- d) Click Protocols White List.
- 5. In the **Protocols White List** dialog box, do the following:
  - a) Under **Users**, click **Add**. In the **Select Users or Groups** dialog box, in the **Enter the object names to select** box, type **Administrators**, and then click **OK**.
  - b) Under Users, select Administrators, and then, under Rules, click Add. In the Add Rule dialog box, in the Description box, specify the rule name. Next, under Web Mail services, select the Gmail check box, and then click OK.

ers:	Rules:	
Users A	Description Protocol Hosts Ports	SSL Extra parameters
Administrators	R Allow Gmail Web Mail GMAIL	Allowed
Add Delete	Add Edit Delete	Load Save

- c) Click **OK** or **Apply** to apply the white list settings and close the **Protocols White List** dialog box.
- 6. In the **Permissions** dialog box, click **OK** or **Apply**.

#### Members of the Users group are allowed to use Dropbox:

1. In the console tree, expand **DeviceLock Service**, and then expand **Protocols**.

- 2. Under Protocols, select Permissions.
- 3. In the details pane, right-click **HTTP**, and then click **Set Permissions**.
- 4. In the **Permissions** dialog box, do the following:
  - a) Under Users, click Add. In the Select Users or Groups dialog box, in the Enter the object names to select box, type Users, and then click OK.
  - b) Under **Users**, select **Users**.
  - c) Under **User's Rights**, select the check boxes next to the following rights: **Generic: Send/Receive Data** and **SSL: Send/Receive Data**.

🖉 Permissions	?	×
Protocol(s): HTTP Computer Name: Local Computer		
Users	€ 🎯	[
2 Users	12 • 2 • 4 • 6 • 8 • 10 • 12 • 2 • 4 • 6 • 8 • 10 • 12	2
	Al	
	Sunday	
Add Delete Set Default	Monday	
User's Rights Allow	Tuesday	
Generic     Section Data	Wednesday	
POST Requests	Thursday	
Sendification Data	Friday	
POST Requests	Saturday	
	Allowed Time      Denied Time	
	Protocols White List	
	OK Cancel Apply	

- d) Click Protocols White List.
- 5. In the **Protocols White List** dialog box, do the following:
  - a) Under Users, click Add. In the Select Users or Groups dialog box, in the Enter the object names to select box, type Users, and then click OK.
  - b) Under Users, select Users, and then, under Rules, click Add.
- 6. In the **Add Rule** dialog box, do the following:
  - a) In the **Protocol:** list, click **SSL**.
  - b) In the **Description** box, specify the rule name.
  - c) In the Hosts: box, type the DNS names of the Dropbox servers separated by a comma or semicolon: www.dropbox.com;
     \*-static.reverse.softlayer.com; \*.compute-1.amazonaws.com.

		_
Protocol:	SSL	
Description:	Allow Dropbox	
Hosts:		
Example:	www.mydomain.com: *.myhost.net: 12.13.14.15:	
unum der	anhou const static services colliner const constant.	
www.dro	oppox.com; *-stauc.reverse.softlayer.com; *.compute-1.	a
mazonav	ws.com	
mazonav	ws.com	×.
mazonav	ws.com	×.
Ports:	as. 2025. 2025	×
Ports: Example:	25; 2025-2035	<u>×</u>
Ports: Example:	25; 2025-2035	<
Ports: Example:	25; 2025-2035	<   >

sers:	Rules:					
Users 🔺	Description	Protocol	Hosts	Ports	SSL	Extra paran
Users	ব্ Alow Dropb	ox 55L	www.dropbox.com;			
Add Delete	Add	Edit Delete			Load	Save

- 7. Click **OK** or **Apply** to apply the white list settings and close the **Protocols White List** dialog box.
- 8. In the **Permissions** dialog box, click **OK** or **Apply**.

**Note:** Access control, audit, shadow copying and content filtering will be disabled for all Dropbox file transfers.

# **Content-Aware Rules Examples**

All users are denied the right to copy to devices (Floppy, Removable) and transmit over the network (over HTTP, FTP, SMTP, Web Mail) the following types of content: files containing more than 1 credit card number, password-protected documents and archives, files containing more than 1 Social Security number, and images containing a large amount of text.

- 1. In the console tree, expand **DeviceLock Service**, expand **Devices**, right-click **Content-Aware Rules**, and then click **Manage**.
- In the Content-Aware Rules for Devices dialog box, under Content Database, click the drop-down arrow next to Add Group, and then click Document Properties.

- 3. In the **Add Document Properties Group** dialog box, do the following:
  - a) In the Name box, specify the name of the group, for example, Passwordprotected documents and archives.
  - b) Select the **Password protected** check box.
  - c) Click OK.

The new content group you created is added to the existing list of content groups under Content Database in the Content-Aware Rules for Devices dialog box. This group will be used to control access to password-protected documents and archives.

- 4. In the **Content-Aware Rules for Devices** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Document Properties**.
- 5. In the Add Document Properties Group dialog box, do the following:
  - a) In the **Name** box, specify the name of the group, for example, **Images contain 70%text**.
  - b) Select the **Contains text** check box and specify **70 %**.
  - c) Click OK.

The new content group you created is added to the existing list of content groups under Content Database in the Content-Aware Rules for Devices dialog box. This group will be used to control access to images containing a large amount of text.

- 6. In the **Content-Aware Rules for Devices** dialog box, under **Content Database**, click the drop-down arrow next to **Add Group**, and then click **Complex**.
- 7. In the Add Complex Group dialog box, do the following:
  - a) In the **Name** box, specify the name of the group, for example, **Complex Group 1**.
  - b) Click Add. In the Content Groups dialog box, select the following groups: Credit Card Number, Images, CAD & Drawing, Images contain 70%text, Password-protected documents and archives, and US Social Security Number.

You can select these groups simultaneously by holding down the CTRL key while clicking them.

c) Compose the following logical expression: US Social Security Number OR Password-protected documents and archives OR Credit Card Number OR Images, CAD & Drawing AND Images contain 70%text.

R Add Com	plex Group					? 🛛
Name:	Complex Group 1					
Description:	Credit cards, SSN,	images, password-	protected docume	nts and archives		
Add 1	nsert View	Dejete				
NOT	(		Criteria			) AND/OR
		US	Social Security Nur	mber		OR
		Password-pro	otected documents	and archives		OR
		1	Credit Card Number	t		OR
		Im	ages, CAD & Draw	ing		AND
		Im	ages contain 70%	ext		
Result US Social S CAD & Drav	ecurity Number OR F wing AND Images co	Password-protected intain 70%text	d documents and a	rchives OR Credit	Card Number O	R Images,
Gear	Validate				ОК	Cancel

The new content group you created is added to the existing list of content groups under Content Database in the Content-Aware Rules for Devices dialog box. This group will be used to control access to files containing more than 1 credit card number, password-protected documents and archives, files containing more than 1 Social Security number, and images containing a large amount of text.

- 8. In the **Content-Aware Rules for Devices** dialog box, do the following:
  - a) Under Users, click Add. In the Select Users or Groups dialog box, in the Enter the object names to select box, type Everyone, and then click OK.
  - b) Under **Users**, select **Everyone**. Under **Content Database**, select the **Complex Group 1** content group, and then click **Add**.
- 9. In the Add Rule dialog box, do the following:
  - a) Under **Applies to**, select the **Permissions** check box.
  - b) Under **Device Type(s)**, select the **Floppy** and **Removable** check boxes.
  - c) Under Action(s), select the Deny check box next to Write.

Add Rule	? 🛛
Description: Complex Group	1
Applies to	0
Devices Type(s):	
DVD/CD-ROM Pfloppy Removable	
Actions	
User's Rights	Allow Deny
Read Write	

😫 Content-Aware Rules for Devices					2 🛛
Content Database Description Complex Group 1				Type Complex	
Add Test Group Duplic Content-Aware Rules	ate Add Group	Edit Group	Delete Group	Show: Complex	: <b>M</b>
Users A	Description	Туре	Action(s)	Applies To	Device Type(s)
C Everyone	Complex Group 1	Complex	Deny: Write	Permissions	Floppy, Removable
Add Delete	C Delete Edt			(	Load Save
			(	ок	Cancel Apply

- 10. In the **Content-Aware Rules for Devices** dialog box, click **OK** or **Apply** to apply the rule.
- 11. In the console tree, expand **Protocols**, right-click **Content-Aware Rules**, and then click **Manage**.
- 12. In the **Content-Aware Rules for Protocols** dialog box, do the following:
  - a) Under Users, click Add. In the Select Users or Groups dialog box, in the Enter the object names to select box, type Everyone, and then click OK.

- b) Under **Users**, select **Everyone**. Under **Content Database**, select the **Complex Group 1** content group, and then click **Add**.
- 13. In the **Add Rule** dialog box, do the following:
  - a) Under **Applies to**, select the **Permissions** check box.
  - b) Under **Protocol(s)**, select the **FTP**, **HTTP**, **SMTP**, and **Web Mail** check boxes.
  - c) Under Action(s), select the Deny check box next to Generic: Outgoing Files and SSL: Outgoing Files.

Permissions Shadowing		
PTP     V     VITTP     DrC(JACL Messenger     DRC     JAbber     Mal.ru Agent	SMTP Social Networks Neb Mail Windows Messen Yahoo Messeng	nger er
Actions User's Rights	Allow	Denv
Generic     Outgoing Files     SSL		
Outgoing Files		

licate Add Group	• Edit Gro	Delete Group	Type Complex Show: Com	x
licate Add Group	• Edit Gro	Delete Group	Type Complex Show: Com	x nplex
licate Add Group	Edit Gro	Delete Group	Complex	nplex
licate Add Group	Edit Gro	Delete Group	Show: Corr	nplex
licate Add Group	Edit Gro	up Delete Grou	Show: Com	nplex
Rules				
Description	Type	Action(s)	Applies To	Protocol(s)
ब्द् Complex Group 1	Complex	Deny: Outgoin	Permissions	FTP, HTTP, SMTP,
Delete Edit				Load Save
	Rules Description Complex Group 1 Delete Edt	Rules Description Type Complex Group 1 Complex Delete Edit	Rules       Description     Type     Action(s)       Complex Group 1     Complex     Denry: Outgoin       Delete     Edt	Rules       Description     Type     Action(s)     Applies To       Complex Group 1     Complex     Deny: Outgoin     Permissions       Delete     Edt

14. In the **Content-Aware Rules for Protocols** dialog box, click **OK** or **Apply** to apply the rule.