

z/OS



Infoprint Server User's Guide

z/OS



Infoprint Server User's Guide

Note:

Before using this information and the product it supports, read the information in “Notices” on page 213.

Fifth Edition (November 2002)

This edition applies to these IBM products:

- Version 1, Release 2 of z/OS (product number 5694-A01)
- Version 1, Release 3 of z/OS.e (product number 5655-G52)
- Version 1, Release 1, Modification Level 1 of Infoprint Server Transforms (product number 5697-F51)

This edition applies to all subsequent releases and modifications until otherwise indicated in new editions.

This edition replaces S544-5746-03.

Internet

Visit our home pages:

- <http://www.ibm.com/printers>
- <http://www.ibm.com/servers/eserver/zseries/zos/>

A form for comments is provided at the back of this book. If the form has been removed, you can send comments by fax to 1-800-524-1519 (USA only) or 1-303-924-6873; by e-mail to printpub@us.ibm.com; or by mail to:

IBM Printing Systems Division
Department H7FE Building 004M
Information Development
PO Box 1900
Boulder CO 80301-9191 USA

IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1995, 2002. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures	xi
Tables	xiii
About this book	xv
Who should read this book	xv
How this book is organized	xv
How to read syntax diagrams	xvi
Where to find more information	xvii
Web sites	xvii
Accessing z/OS licensed documents on the Internet.	xviii
Using LookAt to look up message explanations	xix
Preventive Service Planning information	xix
Books	xix
Summary of changes	xxi
Chapter 1. Introducing Infoprint Server	1
Printer Inventory Manager	3
Windows client	4
Print Interface	5
Print Interface with an SAP R/3 application server running on the same z/OS system	9
Print Interface with the SAP R/3 application server running on a remote system	10
Infoprint Server Transforms	12
Transform Manager	13
NetSpool	14
IP PrintWay	16
SNMP subagent	19
Chapter 2. Printing from z/OS UNIX System Services using Infoprint Server commands	23
Online help for Infoprint Server commands.	23
Messages sent from Infoprint Server commands	24
Transforming jobs to AFP format	24
Transforming jobs from AFP format	24
How do you...	25
Print a file?	25
Send a file to an e-mail destination?	25
Print or e-mail files with special requirements?	25
Find out where the printers are?	26
Find out if a file is printing?	26
Cancel an Infoprint Server job?	26
Transform a file to AFP format?	26
Transform a file from AFP format?	27
afp2pcl—Transform AFP or line data to PCL data	28
Format	28
Description	28
Options.	28
Operand	30
Usage notes.	30
Supported MO:DCA-P objects, AFP resources, and line data controls	31

Limitations	32
Examples	32
Environment variables	33
Files	33
Exit values	34
afp2pdf—Transform AFP or line data to PDF data	35
Format	35
Description	35
Options.	35
Operand	37
Usage notes	37
Supported MO:DCA-P objects, AFP resources, and line data controls	39
Limitations	40
Examples	40
Environment variables	41
Files	42
Exit values	42
afp2ps—Transform AFP or line data to PostScript data	43
Format	43
Description	43
Options.	43
Operand	45
Usage notes	45
Supported MO:DCA-P objects, AFP resources, and line data controls	46
Limitations	46
Examples	47
Environment variables	48
Files	48
Exit values	48
cancel—Cancel a print job.	50
Format	50
Description	50
Operand	50
Examples	50
Environment variables	50
Files	51
Exit values	51
Portability	51
lp—Print a file	52
Format	52
Description	52
Options.	52
Operand	54
Results.	54
Sending a file to an e-mail destination	55
Examples	55
Environment variables	59
Files	59
Exit values	59
Portability	60
lpstat—Show printer names and locations and status of print jobs	61
Format	61
Description	61
Options.	62
Operand	63
Examples	63

I
I

Environment variables	64
Files	64
Exit values	64
Portability	65
pcl2afp—Transform PCL data to AFP data	66
Format	66
Description	66
Options.	66
Operand	68
Limitations	68
Examples	68
Environment variables	69
Files	69
Exit values	69
pdf2afp and ps2afp—Transform PDF or PostScript data to AFP data	70
Format	70
Description	70
Options.	70
Operand	76
Usage notes	76
Limitations	76
Examples	77
Environment variables	78
Files	78
Exit values	78
sap2afp—Transform SAP OTF or ABAP data to AFP data	79
Format	79
Description	79
Options.	79
Operand	80
Customization	80
Limitations	81
Examples	81
Environment variables	82
Files	82
Exit values	82
xml2afp—Transform XML to AFP data	83
Chapter 3. Using job attributes	85
Abbreviations	86
Attributes files	86
Creating an attributes file	86
Using an attributes file	86
Job attributes and JCL parameters	87
Attribute listing	87
address-text	87
building-text	88
carriage-control-type	88
chars	88
copies	90
department-text.	90
document-codepage	90
document-format	91
document-type	92
duplex	92
filter-options	93

form-definition	94
forms	95
hold	95
input-tray	95
input-tray-number	96
jes-priority.	97
name-text	97
output-bin	98
output-bin-number.	98
overlay-back	99
overlay-front	99
page-definition	100
print-error-reporting	100
print-queue-name	101
printer-ip-address	101
resource-library	102
room-text	102
shift-out-shift-in	103
sysout-dataset-name	103
sysout-job-id	104
sysout-job-name	104
table-reference-characters	105
title-text	105
x-image-shift-back	106
x-image-shift-front	107
y-image-shift-back	107
y-image-shift-front	108

Chapter 4. Printing from batch applications using DD and OUTPUT JCL statements

statements	109
Printing output using IP PrintWay.	109
Specifying the printer definition name	109
Specifying class, destination, or form	110
Specifying the printer's IP address	110
Sending output to an e-mail destination	110
Transforming output data.	113
Transforming data using the Print Interface subsystem	115
Transforming data using the resubmit for filtering function.	117
JCL parameters	118
JCL parameters for printing with IP PrintWay	118
JCL parameters for transforming AFP and line data to PCL, PostScript, or PDF format	130
JCL parameters for the Print Interface subsystem.	139
JCL parameters for distribution information	143
AFP parameters for remote printing with Infoprint Manager or Infoprint Server.	144
JCL examples.	144
Direct output to IP PrintWay and to a printer by specifying the printer definition name	144
Direct output to IP PrintWay and to a printer by specifying a host name or an IP address	145
Direct output to IP PrintWay and to a printer by specifying DEST, CLASS, or FORMS	145
Direct output to IP PrintWay and to more than one printer or e-mail destination	146
Specify components in the Printer Inventory.	146

	Specify retry values.	147
	Specify retention periods.	147
	Specify AFP resources for printing on a remote PSF system.	148
	Send line data to an e-mail destination as text data	148
	Send line or AFP data to an e-mail destination as PDF data and print the	
	AFP data on an AFP printer.	149
	Send line or AFP data to an e-mail destination as AFP data	149
	Print line or AFP data on a PostScript or PCL printer using the resubmit for	
	filtering function	150
	Print line or AFP data on a PostScript printer using the Print Interface	
	subsystem	151
	Print PostScript, PCL, or PDF data on an IBM AFP printer using the Print	
	Interface subsystem.	152
	Chapter 5. Printing using the AOPPRINT JCL procedure	153
	Sending a file to an e-mail destination	153
	AOPPRINT parameters	153
	AOPPRINT DD statements	154
	AOPPRINT results	155
	AOPPRINT examples	155
	Print a file on the default printer	155
	Print a file on a specified printer	155
	Print multiple copies of a data set	155
	Submit and hold a job	155
	Specify a code page for ASCII jobs	155
	Print with error processing	156
	Print in-stream data.	156
	Send a file to an e-mail destination	156
	AOPPRINT exit values	157
	Chapter 6. Transforming data with the AOPBATCH program	159
	AOPBATCH parameters	159
	AOPBATCH DD statements.	160
	AOPBATCH examples.	161
	Specify transform input and output in MVS data sets, and specify	
	environment variables	161
	Specify transform input in a UNIX file and output in an MVS data set	162
	Specify transform input in an MVS data set and output in a UNIX file	162
	Transform and print data sets	162
	Exit values	162
	Chapter 7. Printing from VTAM applications.	163
	Data-stream support	163
	Transparent data support (SCS data stream)	164
	Double-byte character set (DBCS) support	164
	Binary data support.	164
	Data-stream restrictions	164
	Data encryption and compression	165
	Differences from SNA network printing.	165
	End-of-file processing	166
	Page formatting for SCS data streams.	166
	Sending output to an e-mail destination	168
	Chapter 8. Printing from Windows systems	169
	Determining the print submission protocol	169
	Installing Infoprint Port Monitor for Windows.	170

I	Before you begin.	170
	Steps for installing Infoprint Port Monitor for Windows	170
	Adding a z/OS printer to your Windows system	171
	Adding a local printer and configuring the Infoprint Port Monitor for Windows	172
	Adding a network printer	175
	Adding an Internet printer	176
	Steps for defining a printer as an Internet printer on Windows 2000 and Windows XP systems	176
	Customizing the AFP Printer Driver	177
I	Sending a file to an e-mail destination	177
	Printing files	178
	Printing from a Windows application	178
I	Using the print command.	179
	Using the LPR command.	179
	Uninstalling the Infoprint Port Monitor for Windows	180
I	Steps for uninstalling Infoprint Port Monitor Version 2.0.0 and later	180
I	Steps for uninstalling Infoprint Port Monitor Version 1.0 on Windows 98 Systems	180
I	Steps for uninstalling Infoprint Port Monitor Version 1.0 on Windows NT and Windows 2000 systems	182
	Chapter 9. Printing from remote non-Windows systems	185
	Submitting a print request	185
I	Sending a file to an e-mail destination	186
	Querying a print request	186
	Printing from an AIX workstation	187
	Printing from an OS/2 workstation	188
	Printing from a remote OS/390 or z/OS system	189
	Printing from a VM or z/VM system	189
	Printing from an OS/400 system	189
I	Printing from a Novell NetWare client	192
	Appendix A. Job attributes and JCL parameters valid for different printer types	193
	Appendix B. JCL parameters and corresponding job attributes	195
	Appendix C. NetSpool support for SCS code points	197
I	Presentation Position command	200
I	Presentation Page Media control.	202
I	SCS Set Attribute control.	203
I	Set Horizontal Format (SHF)	204
I	Set Vertical Format (SVF)	205
	Appendix D. NetSpool support for 3270 data streams code points	207
	Command codes.	207
	Control codes	207
	Attribute types.	208
I	Appendix E. Accessibility	211
I	Using assistive technologies	211
I	Keyboard navigation of the user interface.	211
	Notices	213
	Trademarks.	214

Bibliography	217
Infoprint Server	217
Print Services Facility™ for OS/390	217
Advanced Function Presentation (AFP)	217
Infoprint Manager for AIX and Windows	218
z/OS Version 1 Release 2	218
CICS	219
IMS/ESA® Version 6	219
3270 and SNA data streams	219
 Index	 221

Figures

I	1. Infoprint Server and Infoprint Server Transforms system diagram	1
I	2. Printer Inventory Manager	3
	3. Print Interface system diagram	6
I	4. Printing SAP R/3 documents with the SAP R/3 application server running on a z/OS system	9
I	5. Printing SAP R/3 documents with the SAP R/3 application server running on a non-z/OS system	11
	6. Transform Manager and Infoprint Server Transforms system diagram	14
	7. NetSpool system diagram	15
I	8. IP PrintWay system diagram	17
	9. SNMP Subagent system diagram	20
	10. Summary of JCL parameters for all output processed by IP PrintWay	119
	11. Summary of JCL parameters for all line and AFP output to be transformed to PCL, PostScript, or PDF format	131
I	12. SUBSYS parameter for the Print Interface subsystem	139
	13. Summary of JCL parameters for the distribution of output	143
	14. AOPPRINT JCL parameters: format	153

Tables

1.	Summary of Infoprint Server books	xix
2.	How to specify job attributes	85
3.	input-bin-number default mapping.	97
4.	Sending output to an e-mail destination	111
5.	Data transforms	113
6.	Comparison of Print Interface subsystem and the resubmit for filtering function	114
7.	How retry limit and retry time work together	129
8.	Parameters of the DD JCL statement that the Print Interface subsystem supports	141
9.	Parameters of the OUTPUT JCL statement that the Print Interface subsystem supports	142
10.	Printing from Windows systems	169
11.	Comparison of Windows printing protocols	170
12.	Job attributes and JCL parameters validated for the printer	193
13.	JCL parameters and corresponding job attributes	195
14.	SCS code points	197
15.	Presentation Position X'34xnn'	201
16.	Presentation Page Media (2BD2)	202
17.	Presentation Page Media (2BD2) nn (count byte)	202
18.	Presentation Page Media (2BD2) FC (forms control byte)	202
19.	Presentation Page Media (2BD2) SD (source drawer byte)	202
20.	Presentation Page Media (2BD2) DDO (destination drawer offset)	203
21.	Presentation Page Media (2BD2) SD (destination drawer byte)	203
22.	Presentation Page Media (2BD2) DX (destination drawer duplex)	203
23.	SCS Set Attribute (X'28xyy')	203
24.	Set Horizontal Format parameters	204
25.	Set Horizontal Format	205
26.	Set Vertical Format parameters	205
27.	Set Vertical Format convert to PCL.	206
28.	3270 data stream command codes.	207
29.	3270 data stream control codes	207
30.	3270 data stream attribute types	208

About this book

This book describes how to print jobs using these products:

- Infoprint® Server, an element of z/OS™ Version 1 Release 2 (5694-A01) and higher, and an element of z/OS.e™ Version 1 Release 3 (5655-G52) and higher
- Infoprint Server Transforms Version 1 Release 1 Modification Level 1, a separate IBM program product (5697-F51)

With these products, you can do these tasks:

- Submit jobs to Infoprint Server from these operating systems:
 - z/OS UNIX® System Services
 - z/OS, using Job Control Language (JCL)
 - z/OS, using Virtual Telecommunications Access Method (VTAM®) applications (the term *VTAM* refers to the z/OS Communications Server SNA Services element of z/OS)
 - These remote systems with Transmission Control Protocol/Internet Protocol (TCP/IP) installed:
 - Windows®
 - Advanced Interactive Executive (AIX®)
 - IBM® Operating System/2® (OS/2®)
 - OS/390® or z/OS
 - Virtual Machine (VM) or z/VM™
 - OS/400®
 - Novell NetWare
- Query printer names, printer locations, or print job status
- Cancel print jobs
- Transform print jobs to the Advanced Function Presentation (AFP™) data stream using z/OS UNIX System Services commands
- Transform print jobs from the AFP data stream using z/OS UNIX System Services commands

Who should read this book

This book is for anyone who prints or transforms jobs using Infoprint Server.

How this book is organized

This book is divided into these chapters:

- Chapter 1, “Introducing Infoprint Server” on page 1 is an overview of Infoprint Server.
- Chapter 2, “Printing from z/OS UNIX System Services using Infoprint Server commands” on page 23 describes the commands that are used to do these tasks:
 - Submit jobs to Infoprint Server from z/OS UNIX System Services
 - Query jobs and printer definitions
 - Cancel jobs
 - Transform jobs to the AFP data stream
 - Transform jobs from the AFP data stream

- Chapter 3, “Using job attributes” on page 85 lists the Infoprint Server attributes that describe jobs and the documents in them and explains how to use these attributes.
- Chapter 4, “Printing from batch applications using DD and OUTPUT JCL statements” on page 109 describes how to use standard JCL to submit batch jobs to Infoprint Server from z/OS.
- Chapter 5, “Printing using the AOPPRINT JCL procedure” on page 153 describes a JCL procedure for submitting batch print jobs to Infoprint Server from z/OS.
- Chapter 6, “Transforming data with the AOPBATCH program” on page 159 describes how to use standard JCL to submit batch transform jobs to Infoprint Server.
- Chapter 7, “Printing from VTAM applications” on page 163 describes concepts that users of VTAM applications, such as Customer Information Control System (CICS®) or Information Management System (IMS™), must understand to use Infoprint Server.
- Chapter 8, “Printing from Windows systems” on page 169 describes how to submit jobs to Infoprint Server from a Windows workstation and how to install the Infoprint Port Monitor for Windows.
- Chapter 9, “Printing from remote non-Windows systems” on page 185 describes how to submit and query jobs from remote AIX, OS/2, OS/390, z/OS, VM, z/VM, and Novell NetWare clients.
- Appendix A, “Job attributes and JCL parameters valid for different printer types” on page 193 shows whether job attributes and JCL parameters are validated for individual printers.
- Appendix B, “JCL parameters and corresponding job attributes” on page 195 lists parameters of the OUTPUT and DD JCL statements and the Infoprint Server job attributes that correspond to them.
- Appendix C, “NetSpool support for SCS code points” on page 197 and Appendix D, “NetSpool support for 3270 data streams code points” on page 207 list the code points in VTAM data streams that Infoprint Server supports.
- Appendix E describes accessibility features of Infoprint Server and Infoprint Server Transforms.

This book also contains a bibliography and an index.

The Infoprint Server glossary is located in *z/OS Infoprint Server Customization*.

How to read syntax diagrams

This section explains the general notations that this book uses in syntax diagrams. For ease of reading, this book breaks some examples into several lines. However, when you enter a command, enter it all on one line. Do not press Enter until you have typed the entire command.

This notation:	Means:	You enter:	For example:	
			This book shows:	You enter:
Apostrophes	String	As shown	SEND '123'	SEND '123'
Bold	Keyword	As shown	CLASS	CLASS
Braces	List of items	The braces and one or more items from the list	{GT10 GT12}	{GT10 GT12}

This notation:	Means:	You enter:	For example:	
			This book shows:	You enter:
Brackets	Optional item	One item or no items	aopstop [now]	aopstop
Comma	Separator	As shown	DISPLAY C,K	DISPLAY C,K
Ellipsis	Repeatable item	One or more items	<i>filename ...</i>	file1 file2
Lowercase	Item the system defines	As shown, in lowercase	lp	lp
Lowercase italics	Variable item	A value for the item	MOUNT <i>devnum</i>	MOUNT A30
Parentheses	List of items	The parentheses and one or more items from the list	(GT10,GT12)	(GT10,GT12)
Special characters	Various symbols	As shown	%filter-options	%filter-options
Underline	Default	The item, or you can omit it	K T <u>REF</u>	K T
Uppercase	Item the system defines	As shown, in uppercase	PRMODE	PRMODE
Vertical bar	UNIX pipe (the output of the first is input to the second)	As shown	ls lp	ls lp
Vertical bar in braces	Required choice	One item	{NOW FOREVER}	FOREVER
Vertical bar in brackets	Optional choice	One item or no items	[PORTNO PRTQUEUE]	PORTNO

Where to find more information

This section describes where to find information related to z/OS, Infoprint Server, and Infoprint Server Transforms.

Web sites

These Web sites contain related information:

This site:	Contains:
http://www.ibm.com/printers/	Information about printing products, including: <ul style="list-style-type: none"> An overview of Infoprint Server, including the same printing scenarios that are in <i>z/OS Infoprint Server Introduction</i> Infoprint Server books and other books related to printing (in PDF format)
http://www.ibm.com/printers/download.html	Downloads for Windows systems, including: <ul style="list-style-type: none"> Infoprint Port Monitor AFP Viewer plug-in AFP Printer Driver Network Printer Manager (NPM) for the Web

This site:	Contains:
http://www.ibm.com/servers/eserver/zseries/zos/	Information about z/OS
http://www.ibm.com/servers/eserver/zseries/zos/bkserv/	z/OS documentation, including: <ul style="list-style-type: none"> • All z/OS books (in PDF and BookManager formats) • Updates from APARs and PTFs
http://www.ibm.com/redbooks	IBM redbooks, including a redbook for Infoprint Server
http://www.ibm.com/servers/eserver/zseries/zos/unix/	Information about z/OS UNIX System Services

Accessing z/OS licensed documents on the Internet

z/OS licensed documentation is available on the Internet in BookManager® and PDF format at the IBM Resource Link™ Web site at:

<http://www.ibm.com/servers/resourceLink>

Licensed documents are available only to customers with a z/OS license. Access to these documents requires an IBM Resource Link user ID and password, and a key code. With your z/OS order you received a Memo to Licensees, (GI10-0671), that includes this key code.

To obtain your IBM Resource Link user ID and password, log on to:

<http://www.ibm.com/servers/resourceLink>

To register for access to the z/OS licensed documents:

1. Sign in to Resource Link using your Resource Link user ID and password.
2. Select **User Profiles** located on the left-hand navigation bar.
3. Select **Request Access to z/OS Licensed books**.
4. Supply the key code where requested and select **Submit**.

If you supplied the correct key code, you will receive confirmation that your request is being processed. After your request is processed, you will receive an e-mail confirmation.

Note: You cannot access the z/OS licensed documents unless you have registered for access to them and received an e-mail confirmation informing you that your request has been processed.

To access the licensed documents:

1. Sign in to Resource Link using your Resource Link user ID and password.
2. Select **Library** located on the left-hand navigation bar.
3. Select **zSeries**.
4. Select **Software**.
5. Select the release of z/OS.

Printed licensed documents are not available from IBM.

You can use the PDF format on either z/OS Licensed Product Library CD-ROM or IBM Resource Link to print licensed documents.

Using LookAt to look up message explanations

LookAt is an online facility that lets you look up explanations for most messages you encounter, as well as for some system abends and codes. Using LookAt to find information is faster than a conventional search because in most cases LookAt goes directly to the message explanation.

You can access LookAt from the Internet at:

<http://www.ibm.com/eserver/zseries/zos/bkserv/lookat/> or from anywhere in z/OS where you can access a TSO/E command line (for example, TSO/E prompt, ISPF, z/OS UNIX System Services running OMVS). You can also download code from the *z/OS Collection* (SK3T-4269) and the LookAt Web site that lets you access LookAt from a handheld computer (Palm Pilot VIIx suggested).

To use LookAt as a TSO/E command, you must have LookAt installed on your host system. You can obtain the LookAt code for TSO/E from a disk on your *z/OS Collection* (SK3T-4269) or from the LookAt Web site's **Download** link.

Preventive Service Planning information

Before installing Infoprint Server, you should review the current Preventive Service Planning (PSP) information, also called the *PSP bucket*. You should also periodically review the current PSP information. The PSP upgrade ID is: ZOSV1R2. The subset for Infoprint Server is: INFOPRINT.

To obtain the current PSP bucket, contact the IBM Support Center or use z/OS SoftwareXcel (IBMLink). If you obtained z/OS as part of a CBPDO, HOLDDATA and PSP information is included on the CBPDO tape. However, this information might not be current if the CBPDO tape was shipped several weeks prior to installation.

Books

See "Bibliography" on page 217 for a list of the books referred to in this book, and for books that contain additional information about related products. For titles and order numbers of the books for *all* products that are part of z/OS, see *z/OS Information Roadmap*.

Infoprint Server for z/OS Implementation Redbook, SG24-6234, is available on the Web at: <http://www.ibm.com/redbooks>

Table 1 summarizes the books in the Infoprint Server product library.

Table 1. Summary of Infoprint Server books

Book	Form number
<i>z/OS Infoprint Server Introduction</i>	S544-5742
Introduces all components of Infoprint Server, including IP PrintWay™, NetSpool™, and Print Interface. It also introduces Infoprint Server Transforms. This book contains printing scenarios that show how you can use Infoprint Server in your installation.	
<i>z/OS Infoprint Server Migration</i>	G544-5743
Summarizes the new functions in Infoprint Server and Infoprint Server Transforms and describes the migration tasks required to implement each new function in your installation. It also describes the Infoprint Server migration program, which converts IP PrintWay, NetSpool, and Print Interface printer information to the format required by Infoprint Server for OS/390 V2R8 and higher.	

Table 1. Summary of Infoprint Server books (continued)

Book	Form number
<p><i>z/OS Infoprint Server Customization</i></p> <p>Describes customization tasks for all components of Infoprint Server, including IP PrintWay, NetSpool, and Print Interface. It also describes customization tasks for Infoprint Server Transforms. This book describes required environment variables, configuration files, startup procedures, how to write exit routines and filter programs, and how to use the Infoprint Server API.</p>	S544-5744
<p><i>z/OS Infoprint Server Operation and Administration</i></p> <p>Describes operator procedures and administrative tasks for all components of Infoprint Server, including IP PrintWay, NetSpool, and Print Interface. This book describes how to start and stop Infoprint Server and how the operator can manage the IP PrintWay transmission queue. It describes how the administrator can create entries in the Printer Inventory using either ISPF panels or the Printer Inventory Definition Utility (PIDU) program, define NetSpool printer LUs to VTAM, and use accounting records written by IP PrintWay.</p>	S544-5745
<p><i>z/OS Infoprint Server User's Guide</i></p> <p>Describes how to submit print jobs from remote systems (including Windows systems), the local z/OS system, and Virtual Telecommunications Access Method (VTAM) applications. It describes these z/OS UNIX commands: afp2pcl, afp2pdf, afp2ps, cancel, lp, lpstat, pcl2afp, pdf2afp, ps2afp, and sap2afp; the AOPPRINT JCL procedure; the AOPBATCH program; DD and OUTPUT JCL parameters supported by Infoprint Server; and how to download and install the Infoprint Port Monitor for Windows.</p>	S544-5746
<p><i>z/OS Infoprint Server Messages and Diagnosis</i></p> <p>Describes messages sent by all components of Infoprint Server, including IP PrintWay, NetSpool, and Print Interface. It also describes Infoprint Server Transforms messages and how to use Infoprint Server tracing facilities to diagnose and report errors.</p>	G544-5747

Summary of changes

Summary of changes for S544–5746-04 z/OS Version 1 Release 2

This book contains information previously presented in S544-5746-03, which supports z/OS Version 1 Release 2.

New information

- Information has been added about Infoprint XML Extender for z/OS.
- The description of the **printer-ip-address** job attribute and the **DEST=IP JCL** parameter state that Infoprint Server does not currently support the colon-hexadecimal format of an IP address introduced in z/OS Communications Server Version 1 Release 4.

Deleted information

- Support for Windows 95 has been removed because Microsoft® no longer supports Windows 95.

This book contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

You might notice changes in the style and structure of some content in this book—for example, headings that use uppercase for the first letter of initial words only, and procedures that have a different look and format. The changes are ongoing improvements to the consistency and retrievability of information in our books.

Summary of changes for S544–5746-03 z/OS Version 1 Release 2

This book contains information previously presented in S544-5746-02, which supports z/OS Version 1 Release 2.

This book describes functions that have been added in PTFs after the initial release of z/OS V1R2. Make sure that your installation has applied these Infoprint Server PTFs; otherwise, some information in this book might not be accurate for your system:

- PTF UW85178
- PTF UW87698
- PTF UW88108
- PTF UW88209

New information

- Batch applications can now use the new Print Interface subsystem. The Print Interface subsystem can automatically transform data from one data format to another before writing the output to the JES spool. These sections describe this support:
 - “Transforming output data” on page 113 compares the different methods you can use to transform data, including the Print Interface subsystem.

- “Transforming data using the Print Interface subsystem” on page 115 describes how to use the Print Interface subsystem.
- “JCL parameters for the Print Interface subsystem” on page 139 describes how to code the required SUBSYS parameter on the DD JCL statement.
- These JCL examples show how to use the Print Interface subsystem:
 - “Print line or AFP data on a PostScript printer using the Print Interface subsystem” on page 151
 - “Print PostScript, PCL, or PDF data on an IBM AFP printer using the Print Interface subsystem” on page 152
- Appendix A, “Job attributes and JCL parameters valid for different printer types” on page 193 lists the JCL parameters for which the administrator can specify supported values. Before the Print Interface subsystem accepts data sets to print, it validates that the values specified in these JCL parameters are supported values.
- Appendix B, “JCL parameters and corresponding job attributes” on page 195 lists all Infoprint Server job attributes that you can specify when you use the Print Interface subsystem, including those that do not have corresponding JCL parameters.
- Infoprint Port Monitor Version 2.0.0 can run on the Windows XP and Windows Me systems, in addition to Windows 98, Windows NT, and Windows 2000 systems. These sections describe Infoprint Port Monitor Version 2.0.0:
 - “Installing Infoprint Port Monitor for Windows” on page 170 describes how to install the Infoprint Port Monitor.
 - “Adding a local printer and configuring the Infoprint Port Monitor for Windows” on page 172 describes how to add a Windows printer and configure an Infoprint Port, including how to select the new **Unattended port** option.
 - “Uninstalling the Infoprint Port Monitor for Windows” on page 180 describes how to uninstall the Infoprint Port Monitor.
- Chapter 3, “Using job attributes” on page 85 describes three new Infoprint Server job attributes that let you specify the data set name, job ID, and job name for data sets that Infoprint Server creates to print your documents. The data set name is used as the name of an the e-mail attachment when you send a document to an e-mail destination instead of to a printer.
 - **sysout-dataset-name**
 - **sysout-job-id**
 - **sysout-job-name**

Deleted information

- Infoprint Port Monitor Version 2.0 no longer writes temporary files. Therefore, information about how to specify a directory for Port Monitor temporary files has been removed.

This book contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

Summary of changes for S544–5746-02 z/OS Version 1 Release 2

This book contains information previously presented in S544-5746-01, which supports z/OS Version 1 Release 2.

New information

- Information is added to indicate this book supports z/OS.e.
- IP PrintWay now lets you send print output to an e-mail destination instead of to a printer. These sections describe how to send print output to an e-mail destination using different print submission methods:
 - **lp** command:
 - “Sending a file to an e-mail destination” on page 55
 - “Send files to an e-mail destination” on page 58
 - DD and OUTPUT JCL statements:
 - “Sending output to an e-mail destination” on page 110
 - “Send line data to an e-mail destination as text data” on page 148
 - “Send line or AFP data to an e-mail destination as PDF data and print the AFP data on an AFP printer” on page 149
 - “Send line or AFP data to an e-mail destination as AFP data” on page 149
 - AOPPRINT JCL procedure:
 - “Sending a file to an e-mail destination” on page 153
 - “Send a file to an e-mail destination” on page 156
 - VTAM applications: “Sending output to an e-mail destination” on page 168
 - Windows systems: “Sending a file to an e-mail destination” on page 177
 - Non-Windows remote systems: “Sending a file to an e-mail destination” on page 186
- “title-text” on page 105 describes the **title-text** job attribute, which you can now use to specify a title for an e-mail and a title that a printer’s LPD can print on a separator page.
- “JCL parameters for printing with IP PrintWay” on page 118 describes the TITLE JCL parameter, which you can now use to specify a title for an e-mail and a title that a printer’s LPD can print on a separator page.
- A new appendix describes accessibility features of Infoprint Server and Infoprint Server Transforms.

Changed information

- “Printing from a Novell NetWare client” on page 192 describes how to print from Novell NetWare without using LANRES. z/OS no longer supports LANRES.
- The term *UNIX files* is now used instead of *HFS files* to refer to files that are in any type of hierarchical file system. For example, UNIX files can include files in a DFSMS Hierarchical File System (HFS), a Network File System (NFS), a temporary file system (tfs), or the zSeries™ File System (zFS).
- This book is no longer divided into parts.

Deleted information

- The glossary has been removed and is now located in *z/OS Infoprint Server Customization*.

This book contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

Summary of changes for S544–5746-01 z/OS Version 1 Release 2

This book contains information previously presented in S544-5746-00, which supports z/OS Version 1 Release 1.

New information

- NetSpool now can convert VTAM application print data to PCL format for printing on PCL printers. These sections describe this new support:
 - Chapter 7, “Printing from VTAM applications” on page 163
 - Appendix C, “NetSpool support for SCS code points” on page 197 describes which SCS code points NetSpool supports when it converts SCS data streams to PCL data streams.
 - Appendix D, “NetSpool support for 3270 data streams code points” on page 207 describes which 3270 code points NetSpool supports when it converts 3270 data streams to PCL data streams.
- Print Interface and IP PrintWay now provide enhanced copy support:
 - The **copies** job attribute now lets you specify more than 255 copies, as described in “copies” on page 90.
 - IP PrintWay now can print multiple copies on remote printers that either contain an LPD or support the direct sockets printing protocol. Restrictions about printing copies on these types of printers have been removed.
- “Transform and print data sets” on page 162 shows the JCL required to transform data, save the transformed output to a file, and print the file in the same job.
- The SAP to AFP transform now supports SAP R/3 Release 4.6C, as well as earlier SAP R/3 releases. The SAP to AFP transform produces monochrome output only.
- The AFP to PCL, AFP to PDF, and AFP to PostScript transforms do not support IOCA Color Plus image objects (IOCA FS45), which was recently added to the AFP architecture. Also, the AFP to PCL transform does not support scaling of fonts.

These sections describe these limitations:

 - “afp2pcl—Transform AFP or line data to PCL data” on page 28
 - “afp2pdf—Transform AFP or line data to PDF data” on page 35
 - “afp2ps—Transform AFP or line data to PostScript data” on page 43
- “Using the print command” on page 179 describes how to use the Windows **print** command to print a file to Infoprint Server.
- Chapter 4, “Printing from batch applications using DD and OUTPUT JCL statements” on page 109 describes how to specify the DSNNAME parameter on the DD JCL statement. The DSNNAME parameter can help you to identify your printed output and locate your output data sets on the JES spool.

Changed information

- The **lp** command lets you print only one file at a time if the data must be transformed from one format to another before printing or if files have different data formats. “lp—Print a file” on page 52 describes these limitations.
- The **lpstat** command lets you specify the **-a**, **-o**, **-p**, and **-u** options multiple times. Also, to specify more than one value in these options, you must enclose the values in quotation marks. “lpstat—Show printer names and locations and status of print jobs” on page 61 describes these considerations.
- When you use a z/OS UNIX command to transform data to or from the AFP data stream format and you want to write the output to an MVS data set, you must allocate and catalog the data set prior to running the transform command. If you

use the AOPBATCH procedure to run the transform command, you can allocate the output MVS data set in the AOPBATCH job. These sections describe this requirement:

- “afp2pcl—Transform AFP or line data to PCL data” on page 28
- “afp2pdf—Transform AFP or line data to PDF data” on page 35
- “afp2ps—Transform AFP or line data to PostScript data” on page 43
- “pcl2afp—Transform PCL data to AFP data” on page 66
- “pdf2afp and ps2afp—Transform PDF or PostScript data to AFP data” on page 70
- “sap2afp—Transform SAP OTF or ABAP data to AFP data” on page 79
- “AOPBATCH DD statements” on page 160

Deleted information

- The AFP Printer Driver and AFP Viewer are no longer shipped with Infoprint Server. Therefore, information about how to install them has been removed. However, you can continue to download these programs from the Web at:
<http://www.ibm.com/printers/download.html>
- You can no longer view **man** pages or receive messages in Spanish. Therefore, information about Spanish **man** pages and messages has been removed.

This book contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

Chapter 1. Introducing Infoprint Server

Infoprint Server and Infoprint Server Transforms provide support for LAN and host printing on your z/OS system. Figure 1 shows how most of the components of Infoprint Server and Infoprint Server Transforms fit into your system. The components of Infoprint Server and Infoprint Server Transforms are shaded. If you are viewing the PDF file, components of Infoprint Server are displayed in yellow, while components of Infoprint Server Transforms are displayed in blue. Following the figure is a description of each component.




Figure 1. Infoprint Server and Infoprint Server Transforms system diagram

Printer Inventory and Printer Inventory Manager

The Printer Inventory Manager component of Infoprint Server controls the Printer Inventory. The Printer Inventory consists of files in the hierarchical file system (HFS) that contain information about each printer and each e-mail destination. The Printer Inventory also contains system configuration information for IP PrintWay. As an option, the Printer Inventory can contain system configuration information for PSF for OS/390.

Infoprint Server Windows Client

The Infoprint Server Windows client consists of the Infoprint Port Monitor, which runs on a Windows system and automatically sends print requests and job attributes to the Print Interface component of Infoprint Server running on the z/OS system.

Print Interface

The Print Interface component of Infoprint Server processes print requests from remote clients and from the local z/OS system. Print Interface accepts several different data formats, converts data between EBCDIC and ASCII, transforms data to a format accepted by the printer, and allocates output data sets on the JES spool.

Infoprint Server Transforms

Infoprint Server Transforms, a separate, licensed IBM program product (5697-F51), provides transforms that convert data from one format to another on the local z/OS system.

Transform Manager

The Infoprint Server Transform Manager component of Infoprint Server manages many of the transforms provided by Infoprint Server Transforms and other optional transform products.

NetSpool

The NetSpool component of Infoprint Server processes print requests from VTAM applications, such as CICS and IMS. NetSpool accepts SCS, 3270, and binary data streams, converts SCS and 3270 data streams to either line data streams or PCL data streams, and allocates output data sets on the JES spool.

IP PrintWay

The IP PrintWay component of Infoprint Server transmits data sets from the JES spool to printers or print servers in a TCP/IP or SNA network. IP PrintWay also can transmit data sets to e-mail destinations.

Simple Network Management Protocol (SNMP) subagent (not shown in figure)

The SNMP subagent of Infoprint Server lets you use an SNMP manager to view printer characteristics and printer status for printers controlled by PSF for OS/390 that do not have internal SNMP agents or are not TCP/IP-attached to PSF.

PSF for OS/390 (a separate product)

PSF for OS/390 (5655-B17) is a separate product that can print output on IBM AFP printers. The PSF system programmer can specify PSF printer configuration information in the Printer Inventory that PSF can use when it starts a printer. For information about how to customize PSF to use the Printer Inventory, see *PSF for OS/390 & z/OS: Customization*.

The next sections describe each of the Infoprint Server components in more detail.

Printer Inventory Manager

The Printer Inventory Manager component of Infoprint Server controls the Printer Inventory. The Printer Inventory consists of HFS files that contain information about the printing environment. The administrator must create and manage information in the Printer Inventory.

Note: The Printer Inventory *cannot* be shared by Infoprint Server running at the same or different levels on other systems.

The administrator can create these objects in the Printer Inventory:

- Printer definitions, which contain information about printers and e-mail destinations.
- Printer pool definitions, which contain information about groups of printers and e-mail destinations to which NetSpool can broadcast data.
- FSS definitions, which contain configuration information for IP PrintWay functional subsystems (FSSs). As an option, the administrator can create FSS definitions for PSF for OS/390 FSSs.
- FSA definitions, which contain configuration information for IP PrintWay functional subsystem applications (FSAs). As an option, the administrator can create FSA definitions for PSF for OS/390 FSAs.

Figure 2 shows how the administrator can create definitions in the Printer Inventory and which components of Infoprint Server use the Printer Inventory.




Figure 2. Printer Inventory Manager

1. The administrator can use Infoprint Server ISPF panels and the Printer Inventory Definition Utility (PIDU) to create and maintain the Printer Inventory. The PIDU is useful for creating many printer definitions at the same time and for backing up the Printer Inventory.
2. These Infoprint Server components use information in the Printer Inventory:
 - NetSpool uses information in printer definitions and in printer pool definitions.
 - Print Interface uses information in printer definitions.
 - IP PrintWay uses information in printer definitions. IP PrintWay also uses configuration information in FSS and FSA definitions.

- The SNMP subagent uses printer information that PSF for OS/390 stores in the Printer Inventory about PSF printers.
3. PSF for OS/390, a separate product, can, as an option, use printer configuration information that the PSF system programmer specifies in FSS and FSA definitions in the Printer Inventory.

The printer configuration information in the FSS and FSA definitions is the same as the configuration information that the system programmer can alternatively specify in PSF startup procedures and PSF exits. When the printer configuration information is specified in the Printer Inventory, however, the PSF system programmer can change it without restarting all PSF printers in the PSF functional subsystem (FSS). Only the PSF printers with changed configuration information need to be restarted.

For information about how the PSF system programmer can customize PSF for OS/390 to use the Printer Inventory, see *PSF for OS/390 & z/OS: Customization*.

Additional functions that the Printer Inventory Manager provides are:

- **Migration program**

The Infoprint Server migration program helps the administrator migrate from earlier releases of IP PrintWay, NetSpool, and the OS/390 Print Server. The migration program merges printer information formerly specified in NetSpool print characteristics data sets, NetSpool tables, NetSpool startup procedures, IP PrintWay routing and options data sets, and the Print Interface printer inventory to create entries (such as printer definitions and printer pool definitions) in the new Infoprint Server Printer Inventory.

The migration program can also move printer information located in PSF startup procedures to FSS and FSA definitions in the Printer Inventory.

- **Security**

The administrator must restrict access to the Printer Inventory and to the operator commands that start and stop the Printer Inventory Manager, the Print Interface LPD, the Print Interface IPP server, the Transform Manager, and the SNMP subagent.

Windows client

The Infoprint Server Windows client consists of this program, which runs on Windows 98, NT, 2000, Me, and XP systems:

Infoprint Port Monitor for Windows

The Infoprint Port Monitor for Windows lets users print documents using standard print-submission methods from any Windows application that supports printing. After the Infoprint Port Monitor for Windows is installed and configured on the Windows system, the Port Monitor automatically sends documents to the Print Interface component of Infoprint Server.

Note: Infoprint Server also supports printing from a Windows system with the SMB protocol and the IPP protocol. To use these protocols, Windows users do not need to install the Infoprint Port Monitor for Windows.

These related products also run on Windows systems. Although they are *not* part of the Infoprint Server Windows client, you might want to use them if your installation has IBM AFP printers or AFP documents.

- **AFP Printer Driver for Windows**

The AFP Printer Driver creates output files in AFP format. Files in AFP format can be printed on IBM AFP printers. The AFP Printer Driver can create output files that contain documents, overlays, or page segments. It can also create inline form definitions for printing documents with special options, such as printing on both sides of the paper.

- **AFP Viewer Plug-in for Windows**

The AFP Viewer plug-in lets you view documents in AFP format. For example, documents downloaded from the z/OS system or documents on the Web. The AFP Viewer plug-in also lets you print AFP documents to IBM AFP printers as well as non-AFP printers.

| The Infoprint Port Monitor for Windows is shipped with Infoprint Server. You can
| also download the Infoprint Port Monitor for Windows, the AFP Printer Driver for
| Windows, and the AFP Viewer plug-in for Windows directly to your Windows
| systems from the IBM Printing Systems Division Web site:
| <http://www.ibm.com/printers/download.html>.

Print Interface

The Print Interface component of Infoprint Server processes print requests received from both remote clients and local users. Figure 3 on page 6 shows the steps that occur from the time Print Interface receives a print request until it allocates an output data set on the JES spool. An explanation of each step follows.




Figure 3. Print Interface system diagram

1. Users can submit print requests and query job status from remote clients in the TCP/IP network, using one of these TCP/IP protocols:
 - LPR protocol: The LPR protocol is defined by RFC 1179. Clients that use this protocol include:
 - The Infoprint Port Monitor for Windows. Infoprint Server provides this client.
 - TCP/IP commands such as **lpr**, **enq**, and **lpq**.
 - An SAP R/3 application server that runs on a remote system.
 - Internet Printing Protocol (IPP): IPP is a standard protocol for printing over the Internet. An IPP client must run in the remote system.
 - Server Message Block (SMB) printing protocol: SMB is the standard printing protocol that Windows systems use. The z/OS SMB server must be installed on the z/OS system to receive print requests. The z/OS SMB server uses Print Interface callable services to allocate output data sets on the JES spool and return print job status to the client.
2. Users can submit print requests from the local z/OS system using one of these methods:
 - Print Interface subsystem: Using the Print Interface subsystem, you can transform and print output data created by a batch application with minimal changes to your JCL.

- AOPPRINT: Using the AOPPRINT JCL procedure, you can print existing MVS data sets and UNIX files.
 - z/OS UNIX printing commands (**lp**, **lpstat**, and **cancel**) that Infoprint Server provides: Using these commands, which adhere to the XPG4.2 standard, you can print MVS data sets and UNIX files, query the status of a print job, and cancel a print job. You can run these commands from the z/OS UNIX command line or from a UNIX application.
 - Infoprint Server SAP Output Management System (OMS): Using the Infoprint Server SAP OMS and the SAP R/3 Application Server for z/OS, SAP R/3 users can submit a print job and receive immediate notification about job events.
3. Print Interface runs as a UNIX application that uses the services of z/OS UNIX System Services.
 Print Interface accepts data in any format, including but not limited to these formats: line data, MO:DCA-P (also known as AFP), PostScript, PDF, PCL, SAP (OTF and ABAP), XML, and text.
 4. Each print request specifies the name of a printer definition in the Printer Inventory. The printer definition can describe a printer or an e-mail destination. Print Interface uses information in the printer definition to determine items, such as how to process the data or whether to transform the data.
 5. Print Interface can, in most cases, automatically detect the data format of the input data and validate that the printer accepts that data format. Print Interface can convert data to EBCDIC or ASCII. It can also call transforms provided by Infoprint Server Transforms and other optional transform products to convert data from one data format to another.
 6. For each print request, Print Interface dynamically allocates an output data set on the JES2 or JES3 spool using JES allocation parameters specified in the printer definition, including:
 - JES work-selection parameters, such as class, forms name, and destination. These parameters cause JES to direct the output data sets to the correct JES output writer or functional subsystem application (FSA), such as PSF for OS/390 or IP PrintWay.
 - Advanced Function Presentation (AFP) parameters, such as the name of a form definition and page definition. PSF for OS/390 uses these parameters when printing data on IBM AFP printers.

Some additional functions that Print Interface provides include:

- **Validation of print requests**

Before accepting print requests, Print Interface can validate, with some exceptions, that the document can print as requested on the selected printer. For example, Print Interface can reject documents with data formats that the printer does not support or that are too large to print on the selected printer.

- **Automatic transforms**

Print Interface can, in most cases, automatically detect the input data format and transform data into the format required by the printer or e-mail destination. Print Interface can do these transforms:

- Transform line data (for example, in a sequential data set or a partitioned data set) into text data for printing on a printer such as an IBM network printer.
- Transform text data into line data for printing on an IBM AFP printer.
- Transform PCL, PostScript, PDF, and SAP (OTF and ABAP) data into AFP or line data for printing on an IBM AFP printer. Infoprint Server Transforms is required.

- Transform line data or AFP data into PCL, PostScript, or PDF format. Infoprint Server Transforms is required.
- Transform other data formats using optional transform products such as Infoprint XML Extender for z/OS. XML Extender transforms XML data into AFP data for printing on an IBM AFP printer.
- Transform PCL, PDF, and PostScript data to AFP format on an AIX or Windows system. Infoprint Manager V3R2 for AIX or Infoprint Manager V1R1 for Windows is required. Print Interface can use the color transform provided with Infoprint Manager V3R2 for AIX to transform color PDF and PostScript data to AFP format for printing on an IBM Infoprint Color 130 Plus printer.

- **Notification of completion**

Print Interface can notify users on the local z/OS system when processing of a document is complete and the data set has been removed from the JES spool. It can also notify users who request mail notification with a command, such as **lpr**, that uses the LPR to LPD protocol.

- **Status reporting**

Print Interface can report the status of its data sets that are still on the JES spool. It can report if the data set has been selected for processing, held by the system, retained due to a failed transmission to a LAN printer or an e-mail destination, or deleted before printing.

- **Identification of printed output**

Print Interface retains the user ID of the job submitter for printing on separator pages and for display on the JES spool, so that the user ID can be printed on separator pages and the operator can view the name of the job submitter when the data set is on the JES spool.

- **Double-byte character set (DBCS) support**

Print Interface can convert DBCS data from one code page to another before writing the data to the JES spool.

- **Filter support**

An installation can write a filter program to modify data before Print Interface writes the data to an output data set. A filter can be used to add a separator page or modify data. For example, an installation can write a filter to transform data from one format to another.

- **SAP Output Management System (OMS)**

Print Interface provides an SAP OMS with a Callback daemon to support printing with the SAP R/3 Application Server for z/OS. The OMS and Callback daemon let SAP users print, cancel jobs, obtain job status, and receive immediate notification about job events.

The SAP-certified functions that Print Interface provides are:

- OMS Polling Interface
- OMS/XOM Callback Interface
- OMS Operations Supplement

For more information about SAP certification, visit the SAP Web site at www.sap.com/solutions/compsoft/cspdirectory. “Print Interface with an SAP R/3 application server running on the same z/OS system” on page 9 describes this support.

The Print Interface LPD can print documents received from an SAP R/3 application server running on another system, such as an AIX or Windows NT system. “Print Interface with the SAP R/3 application server running on a remote system” on page 10 describes this support.

Print Interface with an SAP R/3 application server running on the same z/OS system

Figure 4 shows how the Print Interface SAP Output Management System (OMS), Callback daemon, and the SAP R/3 Application Server for z/OS fit into your system. When an SAP R/3 application server runs on the z/OS system, the Print Interface OMS receives print and status requests, and the Callback daemon provides immediate notification of job events. The SAP R/3 Application Server for z/OS and its spool work process must run on the same system as Infoprint Server. The Print Interface Callback daemon can return notification of job events to SAP R/3 application servers running on *other* SAP R/3 systems, provided that the SAP spool work process runs on the z/OS system.




Figure 4. Printing SAP R/3 documents with the SAP R/3 application server running on a z/OS system

1. From an SAP GUI, users make print, cancel, job query, and device query requests to the SAP R/3 Application Server. These print requests specify the name of an SAP R/3 output device defined to the SAP R/3 system. The SAP administrator associates each output device with a printer definition in the Infoprint Server Printer Inventory.

2. For a status request, the Print Interface SAP OMS returns the status of a print job or a list of print jobs that the printer is processing.
3. For a print request, Print Interface detects the data format of the input document and does different processing depending on the type of data:
 - If SAP OTF or ABAP data is to be printed on an AFP printer, Print Interface calls Infoprint Server Transforms to transform the data to AFP format. The SAP to AFP transform uses transform options specified in the printer definition. The administrator must specify the correct transform filter in the printer definition to use transforms.
 - If PCL or PostScript data is to be printed on an IP PrintWay-controlled printer, Print Interface typically does not modify the data. However, the administrator can specify a filter that modifies data in the printer definition.
4. Print Interface creates an output data set on the JES spool. From the JES spool, IP PrintWay, PSF for OS/390, or JES can print the document.
5. IP PrintWay selects data sets from the JES spool and transmits them to remote printers, print servers, or e-mail destinations.
6. PSF for OS/390 selects data sets from the JES spool and prints them on IBM AFP printers. The printers can be local, TCP/IP-attached, or SNA-attached.
7. As print jobs complete (successfully or unsuccessfully), the Print Interface SAP callback daemon sends notification back to the SAP R/3 system.

Print Interface with the SAP R/3 application server running on a remote system

Figure 5 on page 11 shows how the Print Interface LPD and an SAP R/3 application server running on a remote system (such as AIX or Windows NT) fit into your system. When no SAP R/3 application server is running on the z/OS system, the Infoprint Server LPD (as opposed to the Infoprint Server OMS) receives print and status requests, and notification of job events does not occur.




Figure 5. Printing SAP R/3 documents with the SAP R/3 application server running on a non-z/OS system

1. From an SAP GUI, users make print, cancel, job query, and device query requests to an SAP R/3 application server running on a remote system such as Windows NT, AIX, or Solaris. These print requests specify the name of an SAP R/3 output device that is defined to the SAP R/3 system. The SAP administrator associates each output device with a printer definition in the Infoprint Server Printer Inventory.
2. For a status request, the Print Interface LPD returns the status of a print job or a list of print jobs that the printer is processing.
3. For a print request, the Print Interface LPD detects the data format of the input document and does different processing depending on the type of data:
 - If SAP OTF or ABAP data is to be printed on an AFP printer, Print Interface calls Infoprint Server Transforms to transform the data to AFP format. The SAP to AFP transform uses transform options specified in the printer definition. The administrator must configure the printer definition to use transforms and specify transform options.

- If PCL or PostScript data is to be printed on an IP PrintWay-controlled printer, Print Interface typically does not modify the data. However, the administrator can specify a filter that modifies data in the printer definition.
- 4. Print Interface creates an output data set on the JES spool. From the JES spool, IP PrintWay, PSF for OS/390, or JES can print the document, or IP PrintWay can send it to an e-mail destination.
- 5. IP PrintWay selects data sets from the JES spool and transmits them to remote printers or print servers or sends them to e-mail destinations.
- 6. PSF for OS/390 selects data sets from the JES spool and prints them on IBM AFP printers. The printers can be local, TCP/IP-attached, or SNA-attached.

Infoprint Server Transforms

Infoprint Server Transforms is a licensed program product (5697-F51). It provides transforms that convert data from one format to another on the z/OS system. Infoprint Server Transforms consists of these features:

- **Transforms to AFP**

This feature consists of these transforms that convert data streams to monochrome Mixed Object Document Content Architecture for Presentation (MO:DCA-P) data streams, which can be printed on IBM AFP printers:

- PCL to AFP Transform

This transform converts Printer Control Language (PCL) 5e data streams to MO:DCA-P data streams.

- PDF to AFP Transform

This transform converts Adobe Portable Data Format (PDF) 1.2 data streams to MO:DCA-P data streams. (The PDF to AFP transform supports PDF 1.3 except for Compact Font Format support.)

- PostScript to AFP Transform

This transform converts PostScript Language Level 3 data streams to MO:DCA-P data streams.

- SAP to AFP Transform

This transform converts (1) SAP R/3 Release 4.6C (and lower releases) Output Text Format (OTF) data streams to MO:DCA-P data streams and (2) SAP R/3 Release 4.6C (and lower releases) Advanced Business Application Programming (ABAP) data streams to line data streams. IBM AFP printers controlled by PSF can print both MO:DCA-P and line data streams.

- **Kanji AFP Print**

This feature can be used with the PDF to AFP and PostScript to AFP transforms. It lets you print Japanese data streams that use Heisei Kaku Gothic W5 and Heisei Mincho W3 fonts, as well as embedded fonts. These two Heisei fonts, which are provided with this feature, must be installed on the z/OS system. The transform can map some other commonly used Japanese fonts, including Ryumin-Light and Gothic BBB-Medium, to these two Heisei fonts.

- **AFP to PCL Transform**

This transform converts MO:DCA-P and line data streams to PCL 5, 5e, or 5c (color) data streams.

- **AFP to PDF Transform**

This transform converts MO:DCA-P and line data streams to PDF 1.2 (monochrome or color) data streams.

- **AFP to PostScript Transform**

This transform converts MO:DCA-P and line data streams to PostScript Language Level 2 (monochrome or color) data streams.

- **Coax Printer Support**

This feature converts line data streams to Data Stream Compatibility/Data Stream Extended (DSC/DSE) and SNA Character String (SCS) data streams and, with IP PrintWay, transmits the data to VTAM-controlled printers defined as VTAM LU0, LU1, or LU3 printers.

The Transforms to AFP feature and the Kanji AFP Print feature are available at no additional charge to customers who have purchased Infoprint Server. The other features are separately priced features.

A z/OS UNIX command for each transform lets users transform data in a z/OS UNIX file or MVS data set without printing it. The z/OS UNIX transform command creates an output file, which you can print or transmit to another system for viewing or printing. A filter provided for each transform lets Print Interface transform data before writing it to the JES spool. The z/OS UNIX commands and filters are:

afp2pcl, **afp2pdf**, **afp2ps**, **pcl2afp**, **ps2afp**, **pdf2afp**, and **sap2afp**.

For more information about each transform, including its limitations, see Chapter 2, “Printing from z/OS UNIX System Services using Infoprint Server commands” on page 23.

Other transforms: For information about transforms provided by other optional transform products that you can use with Infoprint Server, see the documentation provided with the transform:

- For information about Infoprint XML Extender for z/OS, see *Infoprint XML Extender for z/OS*.

Transform Manager

The Transform Manager component of Infoprint Server controls the transform daemons provided with Infoprint Server Transforms and other optional transform products. The Transform Manager starts and stops the transform daemons using configuration information specified by the administrator. For example, the administrator can limit the number of transform daemons that are active at a time.

Figure 6 on page 14 shows how the Transform Manager and Infoprint Server Transforms and other transform products fit into your system. An explanation of each step follows.




Figure 6. Transform Manager and Infoprint Server Transforms system diagram

1. Print Interface uses transform filters provided by Infoprint Server Transforms and other optional transform products to transform data from one format to another on the z/OS system. The administrator must configure the printer definitions to use the transform filters because by default Print Interface does not transform data. The administrator and users can also specify transform filter options to control the transforms.
2. The z/OS UNIX transform commands provided with Infoprint Server Transforms and other optional transform products let users transform data from one format to another without printing it.
3. The Transform Manager manages the transform daemons and controls how many transform daemons are active at one time. The Transform Manager does not manage the SAP to AFP transform and the Coax Printer Support feature of Infoprint Server Transforms because they are not implemented as daemons.
4. The Transform Manager can use transforms provided by these separate, licensed IBM program products:
 - Infoprint Server Transforms (5697-F51), which transforms data to and from the AFP data format. For information, see “Infoprint Server Transforms” on page 12.
 - Infoprint XML Extender for z/OS (5655-J66), which transforms XML data to AFP format. For information, see *Infoprint XML Extender for z/OS*.

NetSpool

The NetSpool component of Infoprint Server intercepts print data from VTAM applications, such as CICS and IMS, converts the data into line data, and creates output data sets on the JES2 or JES3 spool. You can configure NetSpool so that you do not need to change existing VTAM applications. That is, existing VTAM applications can send print requests to NetSpool in the same manner as they currently send print requests to SNA network printers.

Figure 7 on page 15 shows the steps that occur from the time VTAM applications send print requests to NetSpool printer logical units (LUs) until NetSpool allocates output data sets on the JES spool. An explanation of each step follows.




Figure 7. NetSpool system diagram

1. VTAM applications, such as CICS or IMS, establish communication sessions with NetSpool printer logical units (LUs) instead of with SNA-network printers. Each NetSpool printer LU must be defined to VTAM as an application logical-unit (LU).

NetSpool can process these types of VTAM data streams:

- SNA character string (SCS) data over an LU type 1 session
- 3270 data over an LU type 3 or LU type 0 session
- A binary data stream over an LU type 0, type 1, or type 3 session

2. NetSpool runs as a VTAM application on the same or different z/OS system. Multiple instances of NetSpool can run simultaneously in separate address spaces. Each instance of NetSpool can process VTAM print requests sent to different NetSpool printer LUs.
3. Each NetSpool printer LU must be defined in a printer definition or in a printer pool definition in the Printer Inventory. NetSpool uses information in the printer definition to format data into lines and pages, create either a line data stream or a PCL data stream, and group the data into output data sets.
4. NetSpool dynamically allocates output data sets on the JES2 or JES3 spool using JES allocation parameters specified in the printer definition, including:
 - JES work-selection parameters, such as class, forms name, and destination. These parameters cause JES to direct the output data sets to the correct JES output writer or functional subsystem application (FSA), such as PSF for OS/390 or IP PrintWay.
 - Advanced Function Presentation (AFP) parameters, such as the name of a form definition and page definition. PSF for OS/390 uses these parameters when printing data on IBM AFP printers.

- Distribution information, such as name and address, which can be printed on output header pages.

Additional functions that NetSpool provides are:

- **Operator control**

The system operator can control NetSpool processing from the system console and from extended MCS consoles by issuing NetSpool commands while NetSpool is running. The operator can start and stop individual printer LUs and display the status of printer LUs. To assist in managing data sets from the console, the names of the output data sets created by NetSpool identify the VTAM application that generated the print request.

- **SCS and 3270 data stream support**

NetSpool can convert SCS and 3270 data streams into line data streams or PCL data streams. For information about how NetSpool supports SCS and 3270 data streams, see Appendix C, “NetSpool support for SCS code points” on page 197 and Appendix D, “NetSpool support for 3270 data streams code points” on page 207.

NetSpool also supports the Transparent (TRN) control in SCS data. The TRN control identifies the start of a transparent data stream.

- **Broadcasting output**

You can print output to several printers at the same time. Also, you can print output and send it to e-mail destinations at the same time. To do this, the administrator creates a printer pool definition in the Printer Inventory. When VTAM application data is printed to the printer pool definition, NetSpool creates multiple output data sets on the JES spool.

- **Installation exits**

NetSpool supports exits written by an installation to customize NetSpool processing. NetSpool exits let you add data to the beginning of an output data set, map graphic escape characters to other printable characters, and modify or delete transparent data in an SCS data stream.

- **Binary data support**

The administrator can request in the printer definition that NetSpool treat the data stream as binary data. NetSpool writes binary data to the output data set as variable length records without formatting the data and without rejecting unsupported commands, orders, or data. This function is useful if you want to pass through all data without change and without including transparent (TRN) controls.

IP PrintWay

The IP PrintWay component of Infoprint Server transmits output data sets from the JES spool to remote printers or print servers and to e-mail destinations, using one of these transmission protocols:

- **LPR:** The LPR protocol is a TCP/IP protocol defined by RFC 1179. An LPD that adheres to RFC 1179 must be running in the remote printer or system.
- **Direct-sockets printing:** The direct sockets printing protocol is a TCP/IP protocol in which data is transmitted directly to a designated port. The remote printer or print server must support direct sockets printing.
- **Internet Printing Protocol (IPP):** IPP is a standard TCP/IP protocol for printing over the Internet. An IPP server must be running in the remote printer or system.
- **Virtual Telecommunications Access Method (VTAM):** IP PrintWay supports printing to any printer that is defined to VTAM as LU type 0, LU type 1, or LU

type 3. Supported output data streams are SNA character string (SCS) and Data Stream Compatible/Data Stream Extended (DSC/DSE). The Coax Printer Support feature of Infoprint Server Transforms is required to print on VTAM-controlled printers.

- E-mail: IP PrintWay can use the z/OS UNIX sendmail function to send your print output to one or more e-mail addresses. IP PrintWay sends the output, which can be in any data format, as an e-mail attachment.

Note: IP PrintWay cannot transmit data sets larger than two gigabytes to a remote LPD. Also, depending on the IP PrintWay options the administrator selects in the printer definition, IP PrintWay might not be able to transmit data sets larger than two gigabytes to a remote printer that uses the IPP or direct-sockets printing protocol, or to e-mail destinations.

Figure 8 shows the steps that occur from the time IP PrintWay selects output data sets from the JES spool until IP PrintWay transmits the data sets to the target destination and then deletes the data sets from the JES spool. An explanation of each step follows.




Figure 8. IP PrintWay system diagram

1. IP PrintWay selects output data sets from the JES spool according to the JES work-selection parameters defined for the IP PrintWay FSA. For example, IP PrintWay might select all data sets in JES output class P.

IP PrintWay can select data sets that were allocated on the JES spool by NetSpool or Print Interface, or submitted from TSO or batch applications. The

data sets can contain line data, ASCII text data, or formatted data, such as PCL, PostScript, SAP, or MO:DCA-P (AFP) data.

2. IP PrintWay runs as a functional subsystem application (FSA) of JES2 or JES3. Several IP PrintWay FSAs can run in one functional subsystem address space (FSS) to handle a high volume of data. However, one PrintWay FSA can transmit data sets to multiple printers or print servers.
3. IP PrintWay uses information in the printer definition in the Printer Inventory to process data sets, select the transmission protocol (LPR, direct sockets, IPP, VTAM, or e-mail), and obtain the address of the target printer. IP PrintWay can also use the IP address of a target printer specified directly on an OUTPUT JCL statement or in an Infoprint Server job attribute.

IP PrintWay recognizes data sets allocated on the JES spool by Print Interface and NetSpool and does not convert data from EBCDIC to ASCII or format the data if Print Interface or NetSpool has already converted data to ASCII. For other data sets, IP PrintWay can convert data between EBCDIC and ASCII, can add a header to each page, and can format data using the carriage-control characters in line data, an FCB, or pagination attributes specified in the printer definition.

IP PrintWay can use transforms to convert data from one format to another. IP PrintWay calls Print Interface, if necessary, to do the transform. For more information about how IP PrintWay calls Print Interface when the printer definition requests a data stream transform, see *z/OS Infoprint Server Operation and Administration*.

4. IP PrintWay maintains a transmission queue to keep track of data sets being processed. This transmission queue contains such items as the status of each transmission and routing information. Using Infoprint Server ISPF panels, the system operator can monitor the status of transmissions, reroute data sets to another printer or e-mail destination, and change transmission options.
5. IP PrintWay transmits data sets to the target system using the protocol selected in the printer definition (LPR, direct sockets, IPP, VTAM, or e-mail). When IP PrintWay transmits data to a VTAM-controlled printer, IP PrintWay uses the Coax Printer Support feature of Infoprint Server Transforms.

IP PrintWay can also transmit LPD options and IPP job attributes to the target LPDs and IPP servers. For example, IP PrintWay can transmit information that the LPD prints on a separator page.

IP PrintWay can retry an unsuccessful transmission for a specified number of times at a specified interval. Retry limits and retry times can be specified in the printer definition and on an OUTPUT JCL statement. In addition to the requested retries, IP PrintWay retries an unsuccessful transmission automatically for a short period of time right after transmission.

Additional functions that IP PrintWay provides include:

- **Retaining jobs on the JES spool**

After successfully transmitting each data set, or after completing the requested number of transmission attempts, IP PrintWay can retain the data set on the JES spool forever or for a period of time. Retention periods can be specified in the printer definition or on an OUTPUT JCL statement.

- **Printer selection using an OUTPUT JCL statement**

On an OUTPUT JCL statement, a user can select the printer definition by specifying either (1) the name of the printer definition in the FSSDATA parameter or (2) the DEST, CLASS, or FORMS parameter (or a combination of these parameters) associated with the printer definition.

Users can also specify the IP address for the target printer directly on the OUTPUT JCL statement, thereby eliminating the need for the administrator to create a printer definition for each printer in the Printer Inventory.

- **Accounting**

For each data set processed, IP PrintWay writes a System Management Facility (SMF) type-6 record, which includes the number of bytes transmitted and the IP address of the target system.

- **Installation exits**

IP PrintWay supports exits written by an installation to customize IP PrintWay processing. For example, an exit can change the IP address of the remote printer, add separator pages, modify SMF accounting records, and notify users of processing events.

- **Maintaining transmission order**

IP PrintWay preserves the order of the data sets on the JES spool when transmitting data sets. IP PrintWay retains this order even if the transmission of the data sets must be retried. If a JES output group contains more than one output data set, IP PrintWay acquires all of the data sets in the output group before transmitting any of them and can transmit these data sets to the printer as a single file. Although the data sets are a single file, each data set starts printing on a new page.

- **Transmitting printer commands**

The administrator can specify printer commands in the printer definition for IP PrintWay to send to the printer before or after the data to be printed. Printer commands can be used to change fonts or switch between simplex and duplex printing.

SNMP subagent

The Infoprint Server SNMP subagent, with support that PSF for OS/390 and the z/OS SNMP agent provide, lets administrators monitor printer characteristics (such as the printer resolution) and printer status (such as paper jams) for any printer controlled by PSF for OS/390. Also, administrators can be notified as soon as an intervention situation (such as a paper jam) occurs on the printer. This support does not let administrators change any printer characteristics.

To monitor PSF printers, the z/OS SNMP agent must be configured and an SNMP manager, such as IBM Network Printer Manager (NPM) for the Web, must be installed.

You can monitor PSF printers that do not contain internal SNMP agents, such as the IBM 3900 printer, and also PSF printers that have internal SNMP agents but are not TCP/IP-attached to PSF. You can also monitor PSF TCP/IP-attached printers that contain internal SNMP agents. However, consider defining PSF printers that have internal SNMP agents directly to the SNMP manager. When you define a printer directly to the SNMP manager, you can also monitor printer statistics and change some printer characteristics. See the documentation for your printers to determine if they have internal SNMP agents.

Figure 9 on page 20 shows how the SNMP subagent fits into your system. An explanation of each step follows.




Figure 9. SNMP Subagent system diagram

1. To monitor PSF printers, you must install an SNMP manager. You can install any SNMP manager that communicates with an SNMP agent that supports the general printer MIB (defined in RFC 1759) and has implemented support for multiple printers defined with one IP address.

One SNMP manager that provides the required support is IBM Network Printer Manager (NPM) for the Web, which is shown in Figure 9. You can download NPM from the IBM Printing Systems Division Web site. Administrators can use a Java®-enabled version of Netscape Navigator or Microsoft Internet Explorer to monitor PSF printers, while the NPM server runs on a Windows NT® system. Note that NPM limits the number of PSF printers an administrator can monitor at the same time. See the NPM online help for the maximum number of printers NPM lets you monitor.

As shown in the figure, the SNMP manager (NPM) can also communicate directly with any TCP/IP-attached printer that contains an internal SNMP agent. This printer can be controlled by PSF, but it is not necessary.

2. The SNMP agent, part of the z/OS Communications Server, communicates with the SNMP manager and with the Infoprint Server SNMP subagent.

3. The Infoprint Server SNMP subagent communicates with PSF for OS/390 through the Printer Inventory. PSF for OS/390 stores printer characteristics and printer status in the Printer Inventory for any printer that has SNMP-reporting enabled. (The administrator enables SNMP reporting in the FSA definition for the PSF printer).

The SNMP subagent transmits the information stored by PSF for OS/390 to the SNMP manager through the z/OS SNMP agent. The SNMP subagent also notifies the SNMP manager immediately when PSF for OS/390 detects a change to printer characteristics or printer status.

4. PSF for OS/390 obtains printer characteristics and printer status from any PSF-controlled printer. The PSF printer can be channel-attached, TCP/IP-attached, or SNA-attached. However, the PSF printer cannot be attached using the Download for OS/390 feature of PSF.

If a PSF-controlled printer is shared with another printing application, and is not connected to PSF when an intervention required situation occurs, PSF cannot report the change in printer status.

Chapter 2. Printing from z/OS UNIX System Services using Infoprint Server commands

This chapter describes the z/OS UNIX printing commands of Infoprint Server and the z/OS UNIX transform commands of Infoprint Server Transforms. It also briefly explains the transform commands that other IBM transform products provide, such as Infoprint XML Extender for z/OS.

Printing commands: These printing commands let you print, query, and cancel the printing of files, and let you send files to an e-mail destination instead of to a printer:

Printing commands	See page
cancel—Cancel a print job	50
lp—Print a file	52
lpstat—Show printer names and locations and status of print jobs	61

Transform commands: These transform commands let you transform data from one data format to another without printing it:

Transform commands	See page
afp2pcl—Transform AFP or line data to PCL data	28
afp2pdf—Transform AFP or line data to PDF data	35
afp2ps—Transform AFP or line data to PostScript data	43
pcl2afp—Transform PCL data to AFP data	66
pdf2afp and ps2afp—Transform PDF or PostScript data to AFP data	70
sap2afp—Transform SAP OTF or ABAP data to AFP data	79
xml2afp—Transform XML to AFP data	83

Using the printing commands, you can print UNIX files and MVS data sets on any printer that your administrator has defined in a printer definition in the Infoprint Server Printer Inventory. You can print on local printers that are attached directly to z/OS, or on remote printers in a TCP/IP or SNA network. Instead of printing, you can use the same printing commands to send the data to any e-mail destination that your administrator has defined in a printer definition.

The printing commands provide enhanced function over the commands of the same name that are described in *z/OS UNIX System Services Command Reference*. For example, when you print on IBM Advanced Function Presentation printers, you can specify options such as duplexing or a special overlay. You can also display the status of your print request, and you can cancel a print request. The printing commands adhere to the UNIX standards in XPG4.2, so you do not need to change the printing commands in your UNIX applications when you port them to z/OS.

Online help for Infoprint Server commands

To get online help about Infoprint Server commands, use the **man** command. You can view man pages only in English. If the correct man pages are not displayed, specify this path on the -M option of the **man** command, or add it to your MANPATH environment variable ahead of other values:

Messages sent from Infoprint Server commands

The Infoprint Server commands send messages to your console. These commands can send messages in English or Japanese. If the messages do not appear in the language you desire, add one of these values to your **NLSPATH** environment variable ahead of the other values in the environment variable:

English /usr/lpp/Printsrv/En_US/%N

Japanese /usr/lpp/Printsrv/Ja_JP/%N

Transforming jobs to AFP format

While Infoprint Server lets you submit data in many different formats, Advanced Function Presentation printers print the AFP data stream.

You can submit non-AFP data streams to AFP printers because an optional product, Infoprint Server Transforms (5697-F51), converts jobs to AFP format. Other optional transform products also convert jobs to AFP format. For example, Infoprint XML Extender for z/OS (5655-J66) transforms Extensible Markup Language (XML) files to AFP format. For more information, see “xml2afp—Transform XML to AFP data” on page 83 and *Infoprint XML Extender for z/OS*.

Documents in AFP format are also called *Mixed Object Document Content Architecture Presentation (MO:DCA-P)* documents.

Usually, you do not have to worry about transforming your data to another format. If Infoprint Server Transforms is installed, Infoprint Server automatically calls the appropriate transform when you submit a print request to a printer definition (for a printer or for an e-mail destination) that your administrator has configured for transformation. You might, however, want to transform a file without printing it in these situations:

- You want to verify that the job can be transformed without errors.
- You intend to print a file many times. In this case, it is more efficient to transform the file once and print the output than to transform the file every time you print it.

Transforming jobs from AFP format

Three features of Infoprint Server Transforms convert jobs from AFP format into PCL, PDF, and PostScript. These features let you print files in AFP format on PCL and PostScript printers, and to transform an AFP file to PDF format for viewing on a workstation. Documents in AFP format are also called *Mixed Object Document Content Presentation Architecture (MO:DCA-P)* documents.

Usually, you do not have to worry about transforming your data. If Infoprint Server Transforms is installed, Infoprint Server automatically calls the appropriate transform when you submit a print request to a printer definition (for a printer or for an e-mail destination) that your administrator has configured for transformation. You might, however, want to transform a file without printing it in these situations:

- You want to verify that the file can be transformed without errors.
- You intend to print a file many times. In this case, it is more efficient to transform the file once and print the output than to transform the file every time you print it.
- You want to present your document on the Web.

How do you...

This section is a guide to the rest of this chapter. It tells you what Infoprint Server command you need to use for a printing task and sends you to the right place to get more information.

Print a file?

To print one or more files, use the **lp** command. For example, to print three copies of `myfile1` and `myfile2` on `Printer2`, which is defined in the Infoprint Server Printer Inventory, enter:

```
lp -d Printer2 -n 3 myfile1 myfile2
```

For more information, see “lp—Print a file” on page 52.

Send a file to an e-mail destination?

To send one or more files to an e-mail destination instead of to a printer, use the **lp** command. Infoprint Server can first transform data in the files into a format that is suitable for viewing; for example, into PDF format.

For example, to send files `myfile1` and `myfile2` to e-mail destination `dept123`, which is defined in the Infoprint Server Printer Inventory, enter:

```
lp -d dept123 myfile1 myfile2
```

The recipients listed in the printer definition receive two separate e-mails.

For more information, see “lp—Print a file” on page 52.

Print or e-mail files with special requirements?

You can use Infoprint Server *job attributes* to describe special requirements. Attributes specify things like these:

- Whether to print on one or both sides of the paper
- Resources like fonts, page definitions, form definitions, and overlays
- Text to print on the separator sheet or the subject of the e-mail

Use the **-o** option of the **lp** command to specify attribute values when you print a file or send a print file to an e-mail destination. For example, you want to print file `special.job` on both sides of the paper that is loaded in input tray top of `Printer2`. You want to print one overlay, `010DD`, on all the front sides of the paper and another, `01EVEN`, on all the back sides. Both overlays reside in a library called `MYOVR.LIBRARY`. Enter:

```
lp -d Printer2 -o "input-tray=top duplex=yes
overlay-front=010DD overlay-back=01EVEN
resource-library=MYOVR.LIBRARY" special.job
```

Instead of entering all the attributes on the command line, you can store them in an attributes file. If the attributes file is called `myatts`, enter:

```
lp -d Printer2 -o attributes=myatts special.job
```

For a list of job attributes and a description of the use and values of each one, see “Attribute listing” on page 87. For information about attributes files, see “Attributes files” on page 86. For information about the **-o** option of the **lp** command, see “lp—Print a file” on page 52.

How Do You...

Find out where the printers are?

Use the **lpstat** command to display printer definition names and locations. For example, to see the names and locations of all printers and e-mail destinations known to Infoprint Server, enter:

```
lpstat -a
```

For more information, see “lpstat—Show printer names and locations and status of print jobs” on page 61.

Find out if a file is printing?

You can also use the **lpstat** command to display the status of an Infoprint Server job. For example, you submitted several files to print and want to know if any of them are printing. To display information about all your jobs submitted to any printer, enter:

```
lpstat
```

You can also use **lpstat** to display printer location and job status at the same time. For example, you printed a file to Printer3 and want to pick it up if it has printed instead of waiting to have it delivered to your output bin. To find out where Printer3 is and whether any job that you submitted to it has printed, enter:

```
lpstat -o Printer3
```

For more information, see “lpstat—Show printer names and locations and status of print jobs” on page 61.

Cancel an Infoprint Server job?

Use the **cancel** command to cancel a job submitted to Infoprint Server. For example, you realize that you need to make some changes in the file that you just sent to print on Printer3.

If you don't remember the Infoprint Server job ID that the **lp** command returned, use the **lpstat** command to display all the jobs that you submitted to Printer3:

```
lpstat -o Printer3
```

Suppose that your job has an ID of 17. To cancel it, enter:

```
cancel 17
```

For more information, see “cancel—Cancel a print job” on page 50.

Transform a file to AFP format?

Infoprint Server automatically transforms files in other formats to the Advanced Function Presentation (AFP) data stream when you submit them to a printer definition that the print administrator has configured to do so. You can also use the **pcl2afp**, **pdf2afp**, **ps2afp**, and **sap2afp** commands to transform files in these formats without printing them:

- Printer Control Language (PCL)
- Portable Document Format (PDF)
- PostScript
- SAP Advanced Business Application Programming (ABAP)
- SAP Output Text Format (OTF)

For example, to transform the PostScript file `myfile.ps` to an AFP file called `myfile.afp`, with each page 5.5 inches long and 4 inches wide, enter:

```
ps2afp -o myfile.afp -l 5.5i -w 4i myfile.ps
```

To submit the PCL file `sample.pcl` to the printer named `Printer1` and transform it automatically, enter:

```
lp -d Printer1 sample.pcl
```

Tip: This example assumes that your administrator has configured the `printer1` printer definition in the Infoprint Server Printer Inventory to use the PostScript to AFP or PCL to AFP transform.

For more information, see:

- “pcl2afp—Transform PCL data to AFP data” on page 66
- “pdf2afp and ps2afp—Transform PDF or PostScript data to AFP data” on page 70
- “sap2afp—Transform SAP OTF or ABAP data to AFP data” on page 79

In addition, the optional Infoprint XML Extender for z/OS (5655-J66) lets you transform Extensible Markup Language (XML) files to AFP format for printing or viewing. For more information, see “xml2afp—Transform XML to AFP data” on page 83.

Transform a file from AFP format?

Your administrator can set up your printer definitions so that if you submit a file in AFP format to a printer or to an e-mail destination that does not support AFP but supports PCL, PDF, or PostScript, Infoprint Server can automatically transform the AFP file to the appropriate format. You can also use the **afp2pcl**, **afp2pdf**, and **afp2ps** commands to transform AFP files into these formats without printing them:

- Printer Control Language (PCL)
- Portable Document Format (PDF)
- PostScript

For example, to transform the AFP file `myfile.afp` to a PostScript file called `myfile.ps`, printed in duplex, enter:

```
afp2ps -j "duplex=yes" -o myfile.ps myfile.afp
```

To submit the AFP file `sample.afp` to the printer named `Printer1`, where `Printer1` is a non-AFP printer, and transform it automatically, enter:

```
lp -d Printer1 sample.afp
```

Tip: This example assumes that your administrator has configured the `printer1` printer definition in the Infoprint Server Printer Inventory to use the AFP to PostScript or AFP to PCL transform.

For more information, see:

- “afp2pcl—Transform AFP or line data to PCL data” on page 28
- “afp2pdf—Transform AFP or line data to PDF data” on page 35
- “afp2ps—Transform AFP or line data to PostScript data” on page 43

afp2pcl—Transform AFP or line data to PCL data

Format

```
afp2pcl [-c transformclass] [-F tracefile] [-i inputcodepage] [-j jobattributes]...
        [-o outputfile] [-T traceoptions] [inputfile ...]
```

Description

The **afp2pcl** command converts an Advanced Function Presentation (AFP) or line data stream file into a Printer Control Language (PCL) 5, 5e, or 5c (color) data stream file. This command is part of the Infoprint Server Transforms product.

Options

Tip: You can use the **filter-options** job attribute with, for example, the **lp** command to pass the **-c transformclass** and **-i inputcodepage** options to the AFP to AFP transform.

-c transformclass

Specifies the name of a transform class that your administrator has defined. The transform class determines options such as:

- The characteristics of the output printer device, such as whether it supports color
- The size of paper in each input tray
- Defaults for page formatting options, such as the default page definition, form definition, and font
- Resource libraries

You do not always have to specify a transform class. If you do need to specify one, however, ask your administrator for the name of a transform class suitable for the printer and the type of job.

-F tracefile

Specifies the file in which to store the trace. This should only be used as instructed by IBM service personnel. For information about this option, see *z/OS Infoprint Server Messages and Diagnosis*.

-i inputcodepage

This option applies only when you transform line data. If you specify this option for AFP data, it is ignored.

This option identifies the code page to which line data is converted before it is transformed. Specify a code page that corresponds to the coded fonts specified in the page definition or in the **chars** job attribute.

To transform line data that is already encoded in the code page that corresponds to the coded fonts, do *not* specify this option. If this option is not specified, line data is not converted before it is transformed. For example, to transform a line data document that specifies coded fonts in the **chars** job attribute and currently prints correctly on an AFP printer, do *not* specify this option.

You must specify this option to correctly transform documents encoded in code pages that do not correspond to the code page for the coded fonts. This is most likely to occur when you transform an ASCII file.

In the **-i** option, you must specify a code page that IBM provides and that the iconv utility supports. For valid code page names, see *z/OS C/C++ Programming Guide*. To find the PSF code page ID for each character set, see *IBM AFP Fonts: Font Summary for AFP Font Collection*. The PSF code page ID and the names of the code pages that IBM provides are different. Be careful to specify the IBM code page value. For example, if you specify one of these coded fonts in the **chars** job attribute, specify **-i IBM-500**:

Coded font	PSF code page ID	IBM code page
40D0, 40F0, 40E0, 4100	T1V10500	IBM-500
60D9 (default font)	T1V10500	IBM-500

Note: When you specify this option, also make sure that the code page specified in the **document-codepage** job attribute correctly identifies the code page in which the input document is encoded. If you do not specify the **document-codepage** attribute, the default is the code page of the locale, which is usually an EBCDIC code page.

-j *jobattributes*

Specifies an option, that is, one or more attribute value assignments in the format *attribute=value*, separated by spaces. You can specify **-j** multiple times. If job attributes are repeated, the last value specified for the attribute is used.

- If a value contains spaces, enclose the value in single or double quotation marks:

```
attribute='value with spaces'
attribute="value with spaces"
```

- If an option contains spaces or characters that might be interpreted by the shell (such as **\$ & () > < | ' "**), enclose the option in single or double quotation marks:

```
-j 'attribute1=value1 attribute2=value2'
-j "attribute='value with spaces'"
-j "attribute=value(1)"
```

For information about how the shell interprets special characters, see *z/OS UNIX System Services User's Guide*.

- If both value and option require quotation marks, do either of these:

- Use two pairs of double quotation marks and place a backslash before each quotation mark that surrounds the value:

```
-j "attribute=\"value with spaces\""
```

- Use different quotation marks around the option and value. For example:

```
-j 'attribute="value with spaces"'
-j "attribute='value with spaces'"
```

Instead of entering a string of attributes on the command line, you can store attributes and values in a file. You use a special attribute called **attributes** to specify the file.

You can specify any of these attributes, which apply to all files to be transformed with the command:

carriage-control-type	chars	document-codepage
document-format	duplex	form-definition

afp2pcl

input-tray-number	output-bin-number	overlay-back
overlay-front	page-definition	resource-library
shift-out-shift-in	table-reference-characters	x-image-shift-back
x-image-shift-front	y-image-shift-back	y-image-shift-front

For more information about the attributes, see “Attribute listing” on page 87.

-o *outputfile*

Specifies the output path and file into which the transform output (that is, PCL data) is written. The transform overwrites any existing data in the output file. If you do not specify an output file, the result is written to standard output (STDOUT).

To specify an MVS data set, such as a sequential or partitioned data set, precede the data set name with *//*. When you specify a fully qualified name, two sets of quotation marks are required. For example, *'''hlq.PDS(MYDOC)'''* or *'''hlq.SEQDS'''*. When you specify a partially qualified name, you only need one set of quotation marks. For example, *'''PDS(MYDOC)'''* or *'''SEQDS'''*.

If you specify an MVS data set, you might need to allocate the data set before you run this command, especially when you transform a large document. Allocate a data set that is large enough to hold the output data stream. The size of the output data stream depends on the complexity of the document. Allocate the output data set with these characteristics:

- Record format: VB
- Record length: 1024 or larger is recommended

-T *traceoptions*

Specifies the trace options. This should only be used as instructed by IBM service personnel. For information about this option, see *z/OS Infoprint Server Messages and Diagnosis*.

Operand

inputfile

Specifies an input file to be transformed. If you specify more than one input file name, the **afp2pcl** command concatenates the files. The results are written to a single output file (if one is specified in **-o**) or to standard output.

If you do not specify an input file, or if you specify a dash (-) for the file name, **afp2pcl** uses standard input.

To specify an MVS data set, precede the data set name with *//*. When you specify a fully qualified name, two sets of quotation marks are required. For example, *'''hlq.PDS(MYDOC)'''* or *'''hlq.SEQDS'''*. When you specify a partially qualified name, you only need one set of quotation marks. For example, *'''PDS(MYDOC)'''* or *'''SEQDS'''*.

Usage notes

- Some properties of the output, such as page size, input tray numbers, and color output, are defined in the configuration file **aopxfd.conf**. Your administrator sets up this file.
- If you specify multiple values of the same option, except for **-j**, **afp2pcl** uses the last value that you specified.
- All AFP resources are transformed into PCL and are included in the output data stream to guarantee resource availability.

- IBM recommends that you print transform output on printers that support PCL 5, 5e or 5c. A printer that supports PCL 5c is required to print color output.
- The document formatting options in your document, such as paper size and duplexing, are converted to PCL commands. However, the interpretation of these commands might vary slightly from printer to printer. Unpredictable results can occur if you request formatting options that are not installed in your printer.
- When transforming line data in UNIX files that contain ANSI or no carriage control characters, you must specify **document-format=line**. If the data has ANSI control characters, also specify **carriage-control-type=ansi**.
- To create output that prints edge-to-edge on capable printers, your administrator must specify a paper name designed for edge-to-edge printing in the transform configuration file.

To use the edge-to-edge paper on a capable printer, ask your administrator which printer definition and input tray to specify.

Some printers do not support edge-to-edge printing. On such printers, documents created for edge-to-edge printing have the outside 50 pels, approximately 4 millimeters, of output cut off.

- Any library that the transform needs to access must be defined to RACF® with universal read access.

Supported MO:DCA-P objects, AFP resources, and line data controls

The AFP to PCL transform supports:

MO:DCA-P objects:

- BCOCA: Bar codes
- FOCA:
 - SBCS: 300-pel raster fonts, fixed metrics, and relative metrics. AFP outline fonts are mapped to equivalent raster fonts.
 - DBCS: 300-pel raster fonts, fixed metrics, and relative metrics. AFP outline fonts are not supported.
- GOCA: All functions
- IM: All functions, in single and double dot, in all rotations
- IOCA:
 - Uncompressed, compressed MMR, G3, G4, RL4, ABIC (non-concatenated), JPEG baseline and extended
 - IDE 1-8, 24 (lookup table)
- Object containers for JPEG, JIFF, and TIFF image objects
- PTOCA1, PTOCA2

AFP resources

- Page definitions
- Form definitions, including conditional processing and basic N_UP processing
- Overlays
- Page segments
- User resource libraries

Line data controls

- Carriage control (ANSI, machine)
- Table reference characters

afp2pcl

- Shift out/shift in DBCS data - SOS1 and SOSI2 and SOSI3 options
- Mixed line data and AFP records (including IDM, IMM)

Limitations

This section lists the items in the AFP architecture that the AFP to PCL transform does not currently support. Because the AFP architecture and PSF continue to be enhanced with new functional capabilities, this list might be incomplete after the publication date. We suggest that you test how your AFP applications print on non-AFP printers to make sure that the transform supports all of the AFP functions that your applications use.

- Internal copy groups.
- IOCA Color Plus image objects (IOCA FS45).
- Outline fonts. If outline fonts are included in your input data streams, the transform can map them to the equivalent AFP raster fonts. Font mapping in the transform uses a mapping table designed for the single-byte fonts in IBM AFP Font Collection (Program Number 5648–B33). Scaling of outline fonts is also not supported. Therefore, the page definition must specify a **RATIO** of 100 or omit the **RATIO** keyword. For information about font mapping, see *z/OS Infoprint Server Customization*.
- Output is generated using a resolution of 300 pels. If the input includes resources (for example, fonts) that are not 300 pels, the resulting output is degraded.

Examples

Transform an AFP file, specifying a transform class and output file

To transform the AFP file `myfile.afp` into a PCL file, using the `us` transform class, and write a file called `myfile.pcl`, enter:

```
afp2pcl -c us -o myfile.pcl myfile.afp
```

Transform an AFP data set, specifying a form definition

To transform the MVS™ data set `AFP(MYFILE)` into a PCL file, using the form definition `F1CP0110`, and write a file called `myfile.pcl`, enter:

```
afp2pcl -j "form-def=f1cp0110 " -o myfile.pcl "'/AFP(MYFILE)'"
```

Transform an AFP file, specifying a form definition and a resource library

To transform the AFP file `myfile.afp` into a PCL file, using the form definition `F1CP0110` that contains references to user-supplied AFP resources, and write a file called `myfile.pcl`, enter this command on one line:

```
afp2pcl -j "form-def=f1cp0110 res-lib={lib1.pseglib lib3.private}"  
-o myfile.pcl myfile.afp
```

Transform and print an AFP data set, specifying a form definition and a resource library

To transform the AFP data set `PROD.AFPOUT(JOB1)` into a PCL file, using the form definition `f1cp0110` that contains references to user-supplied AFP resources, and print the output, enter this command on one line:

```
afp2pcl -j "form-def=f1cp0110 res-lib={lib1.pseglib lib3.private}"  
"'/PROD.AFPOUT(JOB1)'" | lp
```

Transform a job using redirection

To transform the AFP file `input.afp` into the PCL output file called `output.pcl`, enter:

```
afp2pcl < input.afp > output.pcl
```

Note: You can use redirection operators only with UNIX files.

Transform multiple files and concatenate the output

To transform the AFP files `input.01.afp`, `input.02.afp`, ... `input.xx.afp` into one PCL output file called `output.pcl`, enter:

```
afp2pcl -o output.pcl input.01.afp input.02.afp ... input.xx.afp
```

Transform a UNIX file to an MVS data set

To transform the line data file `input.line` into an MVS PCL output data set called `hlq.OUTPUT.PCL(MYDOC)`, enter:

```
afp2pcl -j doc-format=line -o "'/hlq.OUTPUT.PCL(MYDOC)'" input.line
```

Transform an MVS data set, writing the output to a UNIX File

To transform the MVS data set `HLQ.INPUT.LINE(MYDOC)` into an output file called `output.pcl`, enter:

```
afp2pcl -o output.pcl "'/hlq.INPUT.LINE(MYDOC)'"
```

Transform line data, specifying a form definition and a page definition

To transform line data in file `myfile.line` that contains ANSI carriage control characters into PCL format, using the form definition `F1CP0110` and page definition `P1P06362`, and write a file called `myfile.pcl`, enter this command on one line:

```
afp2pcl -j "form-def=f1cp0110 page-def=p1p06362 c-c-t=a doc-format=line"
-o myfile.pcl myfile.line
```

Transform a file containing line data, specifying a form definition and fonts

To transform the line data file `myfile.line` containing machine carriage control characters and table reference characters into a PCL file, using the form definition `F1CP0110`, and write a file called `myfile.pcl`, enter this command on one line:

```
afp2pcl -j "form-def=f1cp0110 c-c-t=m t-r-c=yes chars={60D8 60D0}"
-o myfile.pcl myfile.line
```

Environment variables

The **afp2pcl** command uses these environment variables:

AOPCONF	Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (\$HOME/.aopconf) and the system default configuration file (/etc/Printsrv/aopd.conf). For more information about the configuration file, see <i>z/OS Infoprint Server Customization</i> .
NLSPATH	Names the directory paths that the afp2pcl command searches for message catalogs.

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

For the format of the configuration file, see *z/OS Infoprint Server Customization*.

afp2pcl

Exit values

- | | |
|--------------|--|
| 0 | The data was transformed successfully. |
| >0 | An error occurred. |

afp2pdf—Transform AFP or line data to PDF data

Format

```
afp2pdf [-c transformclass] [-F tracefile] [-i inputcodepage] [-j jobattributes]...
        [-o outputfile] [-T traceoptions] [inputfile]
```

Description

The **afp2pdf** command converts an Advanced Function Presentation (AFP) or line data file into an Adobe Portable Document Format (PDF) 1.2 data stream file. This command is part of the Infoprint Server Transforms product.

Options

Tip: You can use the **filter-options** job attribute with, for example, the **lp** command to pass the **-c transformclass** and **-i inputcodepage** options to the AFP to PDF transform.

-c transformclass

Specifies the name of a transform class that your administrator has defined. The transform class determines options such as:

- The characteristics of the output printer device, such as whether it supports color
- The size of paper in each input tray
- Defaults for page formatting options, such as the default page definition, form definition, and font
- Resource libraries

You do not always have to specify a transform class. If you do need to specify one, however, ask your administrator for the name of a transform class suitable for the printer and the type of job.

-F tracefile

Specifies the file in which to store the trace. This should only be used as instructed by IBM service personnel. For information about this option, see *z/OS Infoprint Server Messages and Diagnosis*.

-i inputcodepage

This option applies only when you transform line data. If you specify this option for AFP data, it is ignored.

This option identifies the code page to which line data is converted before it is transformed. Specify a code page that corresponds to the coded fonts specified in the page definition or in the **chars** job attribute.

To transform line data that is already encoded in the code page that corresponds to the coded fonts, do *not* specify this option. When this option is not specified, line data is not converted before it is transformed. For example, to transform a line data document that specifies coded fonts in the **chars** job attribute and currently prints correctly on an AFP printer, do *not* specify this option.

You must specify this option to correctly transform documents encoded in code pages that do not correspond to the code page for the coded fonts. This is most likely to occur when you transform an ASCII file.

In the **-i** option, you must specify a code page that IBM provides and that the iconv utility supports. For valid code page names, see *z/OS C/C++ Programming Guide*. To find the PSF code page ID for each character set, see *IBM AFP Fonts: Font Summary for AFP Font Collection*. The PSF code page ID and the names of the code pages that IBM provides are different. Be careful to specify the IBM code page value. For example, if you specify one of these coded fonts in the **chars** job attribute, specify **-i IBM-500**:

Coded font	PSF code page ID	IBM code page
40D0, 40F0, 40E0, 4100	T1V10500	IBM-500
60D9 (default font)	T1V10500	IBM-500

Note: When you specify this option, also make sure that the code page specified in the **document-codepage** job attribute correctly identifies the code page in which the input document is encoded. If you do not specify the **document-codepage** attribute, the default is the code page of the locale, which is usually an EBCDIC code page.

-j *jobattributes*

Specifies an option, that is, one or more attribute value assignments in the format *attribute=value*, separated by spaces. You can specify **-j** multiple times. If job attributes are repeated, the last value specified for the attribute is used.

- If a value contains spaces, enclose the value in single or double quotation marks:

```
attribute='value with spaces'
attribute="value with spaces"
```

- If an option contains spaces or characters that might be interpreted by the shell (such as **\$ & () > < | ' "**), enclose the option in single or double quotation marks:

```
-j 'attribute1=value1 attribute2=value2'
-j "attribute='value with spaces'"
-j "attribute=value(1)"
```

For information about how the shell interprets special characters, see *z/OS UNIX System Services User's Guide*.

- If both value and option require quotation marks, do either of these:

- Use two pairs of double quotation marks and place a backslash before each quotation mark that surrounds the value:

```
-j "attribute=\"value with spaces\""
```

- Use different quotation marks around the option and value. For example:

```
-j 'attribute="value with spaces"'
-j "attribute='value with spaces'"
```

Instead of entering a string of attributes on the command line, you can store attributes and values in a file. You use a special attribute called **attributes** to specify the file.

You can specify any of these attributes, which apply to all files to be transformed with the command:

carriage-control-type	chars	document-codepage
document-format	duplex	form-definition

input-tray-number	overlay-back	overlay-front
page-definition	resource-library	shift-out-shift-in
table-reference-characters	x-image-shift-back	x-image-shift-front
y-image-shift-back	y-image-shift-front	

For more information about the attributes, see “Attribute listing” on page 87.

-o *outputfile*

Specifies the output path and file into which the transform output (that is, PDF data) is written. The transform overwrites any existing data in the output file. If you do not specify an output file, the result is written to standard output (STDOUT).

To specify an MVS data set, such as a sequential or partitioned data set, precede the data set name with *//*. When you specify a fully qualified name, two sets of quotation marks are required. For example, `"/'/hlq.PDS(MYDOC)'"` or `"/'/hlq.SEQDS'"`. When you specify a partially qualified name, you only need one set of quotation marks. For example, `"/'/PDS(MYDOC)'"` or `"/'/SEQDS'"`.

If you specify an MVS data set, you might need to allocate the data set before you run this command, especially when you transform a large document. Allocate a data set that is large enough to hold the output data stream. The size of the output data stream depends on the complexity of the document. Allocate the output data set with these characteristics:

- Record format: VB
- Record length: 1024 or larger is recommended

-T *traceoptions*

Specifies the trace options. This should only be used as instructed by IBM service personnel. For information about this option, see *z/OS Infoprint Server Messages and Diagnosis*.

Operand

inputfile

Specifies an input file to be transformed. If you specify more than one input file name, the **afp2pdf** command will fail.

If you do not specify an input file, or if you specify a dash (-) for the file name, **afp2pdf** uses standard input.

To specify an MVS data set, precede the data set name with *//*. When you specify a fully qualified name, two sets of quotation marks are required. For example, `"/'/hlq.pds(MYDOC)'"` or `"/'/hlq.seqds'"`. When you specify a partially qualified name, you only need one set of quotation marks. For example, `"/'/pds(MYDOC)'"` or `"/'/seqds'"`.

Usage notes

- Some properties of the output, such as page size and color, are defined in the configuration file **aopxfd.conf**. Your administrator sets up this file.
- If you specify multiple values of the same option, except for **-j**, **afp2pdf** uses the last value that you specified.
- If your original document or formatting options (for example, form definition or job attributes) requires use of specific media options or printer features, such as generation of multiple copies, duplex, input and output bins, finishing, and jogging, this information is not contained in the PDF document output. However, options such as duplex printing and input bin do interact with other variables to

affect the PDF output. Any formatting that affects the placement of the image on the page is still valid with the AFP to PDF transform. When printing PDF documents, you can use the printer driver options to select printer features.

- All AFP resources are transformed into PDF and are included in the output data stream (this is the default). This guarantees resource availability.

Your administrator can override this by specifying BUILTIN on the AOP_OUTLINES configuration option. When this is specified, font resources are not transformed and included in the data stream. Adobe Acrobat Reader will try to resolve the font references. It is possible that Acrobat will not be able to resolve some characters. However, in many applications BUILTIN will be a preferable mode of creating PDF files, because it can significantly reduce the size of the output PDF file.

- When transforming line data in a UNIX file that contains ANSI or no carriage control characters, you must specify **document-format=line**. If the data has ANSI control characters, also specify **carriage-control-type=ansi**.
- The IBM Document Composition Facility (DCF) program produces AFP documents that contain BookMaster fonts (this is the default). Because BookMaster fonts do not have equivalent outline fonts, the transform cannot map them to outline fonts. To improve the readability of the documents with Adobe Acrobat, IBM recommends that you use these two DCF options when you create AFP documents:
 - @COREFNT(YES)
 - @BOOKFNT(3)

These options tell DCF to create AFP documents that use raster fonts in the AFP Font Collection instead of BookMaster fonts. All raster fonts in the AFP Font Collection have outline equivalents.

- Any library that the transform needs to access must be defined to RACF with universal read access.
- If you want to view PDF data with Adobe Acrobat Reader in the landscape direction, do this when you transform line data:
 - Specify a form definition that specifies these in the COPYGROUP command:
 - PRESENT LANDSCAPE
 - DIRECTION ACROSS
 - CUTSHEET NO (this is the default)
 - Specify a page definition that is suitable for DIRECTION ACROSS printing.
 - Make sure that your administrator sets the AOP_CUTSHEET variable to no in the Infoprint Server transform configuration file, aopxfd.conf. (The default value for the AOP_CUTSHEET variable is no.) For an example of the **afp2pdf** command that you can use, see “Transform a file containing line data for viewing in landscape orientation” on page 41.
- You can use Adobe Acrobat Reader 3.0 or later to view and print the PDF output. These considerations apply when you view and print the PDF output:
 - The printed output might be smaller or larger than expected. For example, the output might be 90% of the original size if the Fit To Page option is selected in the Acrobat Reader Print dialog. To solve this problem, deselect the Fit To Page option. The Fit To Page option is selected as the default in Acrobat Reader 4.0.
 - Transformed PDF images might look different from the original AFP image, depending on your monitor and printer.

- If landscape output has been requested, the PDF document is in landscape format. If you later need portrait output, the PDF output can be rotated using Adobe Acrobat Reader.
- The PDF transform uses the AFP font encoding to create the PDF document. The characters contained in the document might not be the same as the ASCII character mapping available on the keyboard used for PDF viewing.
- The actual appearance of raster fonts using Adobe Acrobat Viewer or Acrobat plug-in can differ from the printed output. For example, in the Acrobat Reader some characters might not appear to be aligned on the character baseline. The appearance might change as higher magnification levels are chosen in Acrobat Reader.

The default setting of the Acrobat Reader is to show all fonts under 6 pixels as Greek, or shaded gray lines. Therefore, some of the AFP output might not be visible in the viewer. To correct this problem, in the Reader select **File** and select **Preferences**. On the **General** page, make sure that **Use Greek text below xx pixels** is not selected.
- PDF output contains a unique page number identification that is assigned during the creation of the PDF output file. This page number might not correspond to the page numbers used in the AFP input document.

Supported MO:DCA-P objects, AFP resources, and line data controls

The AFP to PDF transform supports:

MO:DCA-P objects:

- BCOCA: Bar codes
- FOCA:
 - SBCS: 300-pel raster fonts, fixed metrics, and relative metrics. AFP outline fonts are supported.
 - DBCS: 300-pel raster fonts, fixed metrics, and relative metrics. AFP outline fonts are not supported.
- GOCA: All functions
- IM: All functions, in single and double dot, in all rotations
- IOCA:
 - Uncompressed, compressed MMR, G3, G4, RL4, ABIC (non-concatenated), JPEG baseline and extended
 - IDE 1-8, 24 (lookup table)
- Object containers for JPEG, JIFF, and TIFF image objects
- PTOCA1, PTOCA2

AFP resources

- Page definitions
- Form definitions, including conditional processing and basic N_UP processing
- Overlays
- Page segments
- User resource libraries

Line data controls

- Carriage control (ANSI, machine)
- Table reference characters
- Shift out/shift in DBCS data - SOS1 and SOSI2 and SOSI3 options

- Mixed line data and AFP records (including IDM, IMM)

Limitations

This section lists the items in the AFP architecture that the AFP to PDF transform does not currently support. Because the AFP architecture and PSF continue to be enhanced with new functional capabilities, this list might be incomplete after the publication date. We suggest that you test how your AFP applications print on non-AFP printers to make sure that the transform supports all of the AFP functions that your applications use.

- DBCS outline fonts.
- Internal copy groups.
- IOCA Color Plus image objects (IOCA FS45).
- The AFP to PDF transform formats all output for the size of the paper in the first input tray selected.
- Limitations of searching with Adobe Acrobat Reader:
 - Text that has been generated using AFP GOCA output graphic characters cannot be found.
 - To preserve the output fidelity of a document, corresponding placement of characters is done in the PDF output document, which can result in additional “space” characters in a character string. This restricts the operation of the Adobe find function.
 - The AFP representation of a code page might not match its ASCII representation. This can cause problems searching, especially with raster fonts.

Examples

Transform an AFP job, specifying a transform class and output file

To transform the AFP file `myfile.afp` into a PDF file, using the `us` transform class, and write a file called `myfile.pdf`, enter:

```
afp2pdf -c us -o myfile.pdf myfile.afp
```

Transform an MVS AFP job, specifying a form definition

To transform the MVS AFP data set `AFP(MYFILE)` into a PDF file, using the form definition `F1C10110`, and write a file called `myfile.pdf`, enter:

```
afp2pdf -j "form-def=f1c10110" -o myfile.pdf "'AFP(MYFILE)'"
```

Transform an AFP job, specifying a form definition and a resource library

To transform the AFP file `myfile.afp` into a PDF file, using the form definition `F1C10110` that contains references to user-supplied AFP resources, and write a file called `myfile.pdf`, enter this command on one line:

```
afp2pdf -j "form-def=f1c10110 res-lib={lib1.pseglib lib3.private}"
-o myfile.pdf myfile.afp
```

Transform a job using redirection

To transform the AFP file `input.afp` into the PDF output file called `output.pdf`, enter:

```
afp2pdf < input.afp > output.pdf
```

Note: You can use redirection operators only with UNIX files.

Transform a UNIX file to an MVS data set

To transform the line data file `input.line` into an MVS PDF output data set called `HLQ.OUTPUT.PDF(MYDOC)`, enter:

```
afp2pdf -j doc-format=line -o "'HLQ.OUTPUT.PDF(MYDOC)'" input.line
```

Transform an MVS data set, writing the output to a UNIX file

To transform the MVS data set `hlq.INPUT.LINE(MYDOC)` into an output file called `output.pdf`, enter:

```
afp2pdf -o output.pdf "'HLQ.INPUT.LINE(MYDOC)'"
```

Transform a file containing line data, specifying a form definition and a page definition

To transform the line data file `myfile.line` containing ANSI carriage control characters into a PDF file, using the form definition `F1C10110` and page definition `P1P06362`, and write a file called `myfile.pdf`, enter this command on one line:

```
afp2pdf -j "form-def=f1c10110 page-def=p1p06362 c-c-t=a doc-format=line"
-o myfile.pdf myfile.line
```

Transform a file containing line data for viewing in landscape orientation

To transform the line data file `myfile.line` containing ANSI carriage control characters into a PDF file that you can view with Adobe Acrobat Reader in the landscape direction, enter this command on one line:

```
afp2pdf -j "form-def=f101011a page-def=p1a06462 c-c-t=a doc-format=line"
-o myfile.pdf myfile.line
```

Transform a file containing line data, specifying a form definition, a page definition, and fonts

To transform the line data file `myfile.line` containing machine carriage control characters and table reference characters into a PDF file, using the form definition `F1C10110` and page definition `F1P06362`, and write a file called `myfile.pdf`, enter this command on one line:

```
afp2pdf -j "form-def=f1c10110 page-def=p1p06362 c-c-t=m t-r-c=yes chars={60D8 60D0}"
-o myfile.pdf myfile.line
```

Transform a file containing line data, specifying a page definition and print offset

To transform the line data file `myfile.line` containing machine carriage control characters into a PDF file, using the page definition `P1P06362`, positioning the output 24 millimeters (approximately one inch) from the left edge of the paper, and write a file called `myfile.pdf`, enter this command on one line:

```
afp2pdf -j "page-def=p1p06362 c-c-t=m x-image-shift-front=24" -o myfile.pdf
myfile.line
```

Environment variables

The **afp2pdf** command uses these environment variables:

AOPCONF	Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (<code>\$HOME/.aopconf</code>) and the system default configuration file (<code>/etc/Printsrv/aopd.conf</code>). For more information about the configuration file, see <i>z/OS Infoprint Server Customization</i> .
NLSPATH	Names the directory paths that the afp2pdf command searches for message catalogs.

afp2pdf

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

For the format of the configuration files, see *z/OS Infoprint Server Customization*.

Exit values

- 0** The data was transformed successfully.
- >0** An error occurred.

afp2ps—Transform AFP or line data to PostScript data

Format

```
afp2ps [-c transformclass] [-F tracefile] [-i inputcodepage] [-j jobattributes]...
      [-o outputfile] [-T traceoptions] [inputfile ...]
```

Description

The **afp2ps** command converts an Advanced Function Presentation (AFP) or line data file into a PostScript level 2 data stream file. This command is part of the Infoprint Server Transforms product.

Options

Tip: You can use the **filter-options** job attribute with, for example, the **lp** command to pass the **-c transformclass** and **-i inputcodepage** options to the AFP to PostScript transform.

-c transformclass

Specifies the name of a transform class that your administrator has defined. The transform class determines options such as:

- The characteristics of the output printer device, such as whether it supports color
- The size of paper in each input tray
- Defaults for page formatting options, such as the default page definition, form definition, and font
- Resource libraries

You do not always have to specify a transform class. If you do need to specify one, however, ask your administrator for the name of a transform class suitable for the printer and the type of job.

-F tracefile

Specifies the file in which to store the trace. This should only be used as instructed by IBM service personnel. For information about this option, see *z/OS Infoprint Server Messages and Diagnosis*.

-i inputcodepage

This option applies only when you transform line data. If you specify this option for AFP data, it is ignored.

This option identifies the code page to which line data is converted before it is transformed. Specify a code page that corresponds to the coded fonts specified in the page definition or in the **chars** job attribute.

To transform line data that is already encoded in the code page that corresponds to the coded fonts, do *not* specify this option. When this option is not specified, line data is not converted before it is transformed. For example, to transform a line data document that specifies coded fonts in the **chars** job attribute and currently prints correctly on an AFP printer, do *not* specify this option.

You must specify this option to correctly transform documents encoded in code pages that do not correspond to the code page for the coded fonts. This is most likely to occur when you transform an ASCII file. In the **-i** option, you must specify a code page that IBM provides and that the iconv

utility supports. For valid code page names, see *z/OS C/C++ Programming Guide*. To find the PSF code page ID for each character set, see *IBM AFP Fonts: Font Summary for AFP Font Collection*. The PSF code page ID and the names of the code pages that IBM provides are different. Be careful to specify the IBM code page value. For example, if you specify one of these coded fonts in the **chars** job attribute, specify `-i IBM-500`:

Coded font	PSF code page ID	IBM code page
40D0, 40F0, 40E0, 4100	T1V10500	IBM-500
60D9 (default font)	T1V10500	IBM-500

Note: When you specify this option, also make sure that the code page specified in the **document-codepage** job attribute correctly identifies the code page in which the input document is encoded. If you do not specify the **document-codepage** attribute, the default is the code page of the locale, which is usually an EBCDIC code page.

-j *jobattributes*

Specifies an option, that is, one or more attribute value assignments in the format *attribute=value*, separated by spaces. You can specify **-j** multiple times. If job attributes are repeated, the last value specified for the attribute is used.

- If a value contains spaces, enclose the value in single or double quotation marks:

```
attribute='value with spaces'
attribute="value with spaces"
```

- If an option contains spaces or characters that might be interpreted by the shell (such as `$ & () > < | ' "`), enclose the option in single or double quotation marks:

```
-j 'attribute1=value1 attribute2=value2'
-j "attribute='value with spaces'"
-j "attribute=value(1)"
```

For information about how the shell interprets special characters, see *z/OS UNIX System Services User's Guide*.

- If both value and option require quotation marks, do either of these:

- Use two pairs of double quotation marks and place a backslash before each quotation mark that surrounds the value:

```
-j "attribute=\"value with spaces\""
```

- Use different quotation marks around the option and value. For example:

```
-j 'attribute="value with spaces"'
-j "attribute='value with spaces'"
```

Instead of entering a string of attributes on the command line, you can store attributes and values in a file. You use a special attribute called **attributes** to specify the file.

You can specify any of these attributes to describe the job and all the files in it:

carriage-control-type	chars	document-codepage
document-format	duplex	form-definition
input-tray-number	output-bin-number	overlay-back

overlay-front	page-definition	resource-library
shift-out-shift-in	table-reference-characters	x-image-shift-back
x-image-shift-front	y-image-shift-back	y-image-shift-front

For more information about the attributes, see "Attribute listing" on page 87.

-o *outputfile*

Specifies the output path and file into which the transform output (that is, PostScript data) is written. The transform overwrites any existing data in the output file. If you do not specify an output file, the result is written to standard output (STDOUT).

To specify an MVS data set, such as a sequential or partitioned data set, precede the data set name with *//*. When you specify a fully qualified name, two sets of quotation marks are required. For example, `"/'/hlq.PDS(MYDOC)'"` or `"/'/hlq.SEQDS'"`. When you specify a partially qualified name, you only need one set of quotation marks. For example, `"/'/PDS(MYDOC)'"` or `"/'/SEQDS'"`.

If you specify an MVS data set, you might need to allocate the data set before you run this command, especially when you transform a large document. Allocate a data set that is large enough to hold the output data stream. The size of the output data stream depends on the complexity of the document. Allocate the output data set with these characteristics:

- Record format: VB
- Record length: 1024 or larger is recommended

-T *traceoptions*

Specifies the trace options. This should only be used as instructed by IBM service personnel. For information about this option, see *z/OS Infoprint Server Messages and Diagnosis*.

Operand

inputfile

Specifies an input file to be transformed. If you specify more than one input file name, the **afp2ps** command concatenates the files. The results are written to a single output file (if one is specified in **-o**) or to standard output.

If you do not specify an input file, or if you specify a dash (-) as the file name, **afp2ps** uses standard input.

To specify an MVS data set, precede the data set name with *//*. When you specify a fully qualified name, two sets of quotation marks are required. For example, `"/'/hlq.pds(MYDOC)'"` or `"/'/hlq.seqds'"`. When you specify a partially qualified name, you only need one set of quotation marks. For example, `"/'/pds(MYDOC)'"` or `"/'/seqds'"`.

Usage notes

- Some properties of the output, such as page size, input tray IDs, and color, are defined in the configuration file **aopx.fdf.conf**. Your administrator sets up this file.
- If you specify multiple values of the same option, except for **-j**, **afp2ps** uses the last value that you specified.
- The AFP transform for PostScript converts the document formatting options to corresponding PostScript commands (for example: paper size, input tray, duplexing). The interpretation of these commands depends on your printer.
- All AFP resources are transformed into PostScript and are included in the output data stream. This guarantees resource availability.

- When transforming line data in UNIX files with ANSI or no carriage control characters, you must specify **document-format=line**. If the data has ANSI control characters, you must also specify **carriage-control-type=ansi**.
- To create output that prints edge-to-edge on capable printers, your administrator must specify a paper name designed for edge-to-edge printing in the transform configuration file.

To use the edge-to-edge paper on a capable printer, ask your administrator which printer definition and input tray to specify.

Some printers do not support edge-to-edge printing. On such printers, documents created for edge-to-edge printing have the outside 50 pels, approximately 4 millimeters, of output cut off.
- Any library that the transform needs to access must be defined to RACF with universal read access.

Supported MO:DCA-P objects, AFP resources, and line data controls

The AFP to PostScript transform supports:

MO:DCA-P objects:

- BCOCA: Bar codes
- FOCA:
 - SBCS: 300-pel raster fonts, fixed metrics, and relative metrics. AFP outline fonts are supported.
 - DBCS: 300-pel raster fonts, fixed metrics, and relative metrics. AFP outline fonts are not supported.
- GOCA: All functions
- IM: All functions, in single and double dot, in all rotations
- IOCA:
 - Uncompressed, compressed MMR, G3, G4, RL4, ABIC (non-concatenated), JPEG baseline and extended
 - IDE 1-8, 24 (lookup table)
- Object containers for JPEG, JIFF, and TIFF image objects
- PTOCA1, PTOCA2

AFP resources

- Page definitions
- Form definitions, including conditional processing and basic N_UP processing
- Overlays
- Page segments
- User resource libraries

Line data controls

- Carriage control (ANSI, machine)
- Table reference characters
- Shift out/shift in DBCS data - SOS1 and SOSI2 and SOSI3 options
- Mixed line data and AFP records (including IDM, IMM)

Limitations

This section lists the items in the AFP architecture that the transform does not currently support. Because the AFP architecture and PSF continue to be enhanced

with new functional capabilities, this list might be incomplete after the publication date. We suggest that you test how your AFP applications print on non-AFP printers to make sure that the transform supports all of the AFP functions that your applications use.

- Internal copy groups
- IOCA Color Plus image objects (IOCA FS45)

Examples

Transform an AFP job, specifying a transform class and output file

To transform the AFP file `myfile.afp` into a PostScript file, using the `us` transform class, and write a file called `myfile.ps`, enter:

```
afp2ps -c us -o myfile.ps myfile.afp
```

Transform a file, specifying a form definition

To transform the AFP file `AFP(MYFILE)` into a PostScript file, using the form definition `F1CP0110`, and write a file called `myfile.ps`, enter:

```
afp2ps -j "form-def=f1cp0110" -o myfile.ps "'/AFP(MYFILE)'"
```

Transform a file, specifying a form definition and a resource library

To transform the AFP file `myfile.afp` into a PostScript file, using the form definition `F1CP0110` that contains references to user-supplied AFP resources, and write a file called `myfile.ps`, enter this command on one line:

```
afp2ps -j "form-def=f1cp0110 res-lib={lib1.pseglib lib3.private}"
-o myfile.ps myfile.afp
```

Transform and print an MVS data set, specifying a form definition and a resource library

To transform the MVS data set `PROD.AFPOUT(JOB1)` into a PostScript file, using the form definition `F1CP0110` that contains references to user-supplied AFP resources, and print the output, enter this command on one line:

```
afp2ps -j "form-def=f1cp0110 res-lib={lib1.pseglib lib3.private}"
"/'/PROD.AFPOUT(JOB1)'" | lp
```

Transform a job using redirection

To transform the AFP file `input.afp` into the PostScript output file called `output.ps`, enter:

```
afp2ps < input.afp > output.ps
```

Note: You can use redirection operators only with UNIX files.

Transform multiple files and concatenate the output

To transform the AFP files `input.01.afp`, `input.02.afp`, ... `input.xx.afp` into one PostScript output file called `output.ps`, enter:

```
afp2ps -o output.ps input.01.afp input.02.afp ... input.xx.afp
```

Transform a UNIX file to an MVS data set

To transform the line data file `input.line` into an MVS PostScript output data set called `hlq.OUTPUT.PS(MYDOC)`, enter:

```
afp2ps -j doc-format=line -o "'/hlq.OUTPUT.PS(MYDOC)'" input.line
```

Transform an MVS data set, writing the output to a UNIX file

To transform the MVS data set `hlq.INPUT.LINE(MYDOC)`, where `hlq` is your user ID, into a PostScript output file called `output.ps`, enter:

afp2ps

```
afp2ps -o output.ps "'/'hlq.INPUT.LINE(MYDOC)'"
```

Transform a file containing line data, specifying a form definition and a page definition

To transform the line data file `myfile.line` containing ANSI carriage control characters into a PostScript file, using the form definition `F1CP0110` and page definition `P1P06362`, and write a file called `myfile.ps`, enter this command on one line:

```
afp2ps -j "form-def=f1cp0110 page-def=p1p06362 c-c-t=a doc-format=line"
-o myfile.ps myfile.line
```

Transform a file containing line data, specifying a page definition and fonts

To transform the line data file `myfile.line` containing machine carriage control characters and table reference characters into a PostScript file, using the page definition `P1P06362`, and write a file called `myfile.ps`, enter this command on one line:

```
afp2ps -j "page-def=p1p06362 c-c-t=m t-r-c=yes chars={60D8 60D0}" -o myfile.ps
myfile.line
```

Transform a file containing line data, specifying a page definition and print offset

To transform the line data file `myfile.line` containing machine carriage control characters into a PostScript file, using the page definition `P1P06362`, positioning the output approximately 1 inch from the left edge of the paper, and write a file called `myfile.ps`, enter this command on one line:

```
afp2ps -j "page-def=p1p06362 c-c-t=m x-image-shift-front=24" -o myfile.ps
myfile.line
```

Environment variables

The **afp2ps** command uses these environment variables:

AOPCONF	Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (\$HOME/.aopconf) and the system default configuration file (/etc/Printsrv/aopd.conf). For more information about the configuration file, see <i>z/OS Infoprint Server Customization</i> .
NLSPATH	Names the directory paths that the afp2ps command searches for message catalogs.

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

For the format of the configuration files, see *z/OS Infoprint Server Customization*.

Exit values

0	The data was transformed successfully.
---	--

>0 An error occurred.

cancel—Cancel a print job

Format

cancel *jobid* ...

Description

The **cancel** command cancels one or more print jobs that you submitted, with these restrictions:

- You can only cancel your own jobs.
- You cannot cancel a job after it has started processing.
- In a JES3 environment, you might not be able to cancel a job that is held on the Job Entry Subsystem (JES) spool.

Operand

jobid ...

The Infoprint Server job ID of the print job you want to cancel. If you do not know the Infoprint Server job ID, you can determine it by using the **lpstat** command to query all the jobs that you submitted.

The **lp** command and AOPPRINT JCL procedure return the Infoprint Server job ID to you when a job is accepted for printing. Infoprint Server also can return the Infoprint Server job ID to you when you submit a job from a remote system.

The Infoprint Server job ID is not the same as the z/OS job ID, which the z/OS system assigns to each job on the JES spool. When you submit a job using the Print Interface subsystem, the z/OS job ID is returned to you.

Examples

Cancel jobs

To cancel jobs 3, 5, and 6, enter:

```
cancel 3 5 6
```

Identify a job and cancel it

You submitted a job to print and want to cancel it, but you don't remember the Infoprint Server job ID. Enter:

```
lpstat
```

lpstat returns information about all your jobs, including the Infoprint Server job ID and the names of the files in each job. You identify the job you want to cancel as job 27. To cancel it, enter:

```
cancel 27
```

Environment variables

The **cancel** command uses these environment variables:

AOPCONF Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (**\$HOME/.aopconf**) and the system default configuration file (**/etc/Printsrv/aopd.conf**). For more information about the configuration file, see *z/OS Infoprint Server Customization*.

NLSPATH Names the directory paths that the **cancel** command searches for message catalogs.

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

Exit values

- 0** Infoprint Server accepted the request.
- >0** An error occurred that prevented Infoprint Server from accepting the request. Some possible errors are:
- The command syntax is not valid.
 - Infoprint Server is not available.
 - There was an error in reading the Infoprint Server configuration file.

Portability

There are no extensions to any Portable Operating System Interface for Computer Environments (POSIX) standard or to the XPG4.2 standard for the **cancel** command.

lp—Print a file

Format

lp [-c`msw`] [-d *destination*] [-n *copies*] [-o *option*] ... [-t *title*] [*filename* ...]

Description

The **lp** command prints one or more files, or sends the files to an e-mail destination. The address of the printer, or the e-mail address list, is specified in the printer definition in the Infoprint Server Printer Inventory, which your administrator manages.

The files can be:

- MVS data sets, such as partitioned data sets or sequential data sets
- UNIX files, such as files in a DFSMS Hierarchical File System (HFS), a Network File System (NFS), and a temporary file system (TFS)
- Lists of printable files

If you do not specify any files on the command line, or if you specify a dash (–) for the file name, **lp** prints from standard input.

If Infoprint Server Transforms or another optional transform product is installed, Infoprint Server can automatically transform a file from one data format to another. To transform a file, the administrator must request the transform in the printer definition.

The **lp** command returns an Infoprint Server job ID, which you can use to query or cancel the job.

Options

-c Makes a copy of the file and prints that copy. Copying files lets you change the original files after submitting the **lp** command. The printed file does not contain the changes. **-c** is the default.

-d *destination*

Selects the printer or the e-mail destination. For *destination*, specify the name of a printer definition in the Infoprint Server Printer Inventory. Contact your administrator for the names of printer definitions or use the **lpstat** command to list printer definition names.

You can omit this option if there is a default printer. You can define a default printer by setting the **LPDEST** or **PRINTER** environment variable. The administrator can also define a default printer. If you do not specify a printer and there is no default, the **lp** command displays an error message.

-m Notifies you by electronic mail when the file is removed from the system spool for any reason. Some reasons are:

- The file has finished printing.
- The file has been transmitted to a local area network (LAN) printer or to the z/OS UNIX sendmail function. You might receive notification before the file has finished printing or been sent to the e-mail destination. You might receive notification even though a transmission error has occurred.

If your administrator has requested that Infoprint Server retain files on the system spool after transmission, you receive notification after the retention time expires.

- The operator has deleted the file.

Tip: Notification might be delayed to improve system performance.

-n copies

Prints the specified number of copies of each file. You can specify a value from 1 to 32640. This option overrides the **copies** job attribute. The default value is the copies value in the printer definition, or, if none is specified, one copy.

Tip: VTAM-controlled printers and some IPP-enabled printers do not support printing more than one copy. In this case, only one copy prints. This option is ignored when data is sent to an e-mail destination. In this case, only one copy is sent.

-o option

Specifies an option, that is, one or more attribute value assignments in the format *attribute=value*, separated by spaces.

- If a value contains spaces, enclose the value in single or double quotation marks:

```
attribute='value with spaces'
attribute="value with spaces"
```

- If an option contains spaces or characters that can be interpreted by the shell (such as **\$ & () > < | ' " #**), enclose the option in single or double quotation marks:

```
-o 'attribute1=value1 attribute2=value2'
-o "attribute='value with spaces'"
-o "attribute=value(1)"
```

For information about how the shell interprets special characters, see *z/OS UNIX System Services User's Guide*.

- If both value and option require quotation marks, do either of these:

- Use two pairs of double quotation marks and place a backslash before each quotation mark that surrounds the value:

```
-o "attribute=\"value with spaces\""
```

- Use different quotation marks around the option and value. For example:

```
-o 'attribute="value with spaces"'
-o "attribute='value with spaces'"
```

For a list of the attributes you can specify to describe the job and all the files in it, see “Attribute listing” on page 87.

Instead of entering a string of attributes on the command line, you can store attributes and values in a file. You use a special attribute called **attributes** to specify the file. For examples, see “Specify the attributes files” on page 57 and “Creating an attributes file” on page 86.

You can also set the **AOOPTIONS** environment variable to a string of attributes and values. The **lp** command treats these attributes as if you had specified them before any other values of the **-o** option on the command

lp

line. For an example of using the **AOOPTIONS** environment variable, see “Specify the AOPTIONS environment variable” on page 57.

If you specify an attribute more than once, the **lp** command uses the last value.

-s Suppresses the message that the **lp** command returns when Infoprint Server has accepted the request. This message contains the Infoprint Server job ID. You must know the job ID to query or cancel the job.

-t *"description of file"*

Describes the file, which can be printed as the title on a separator page, a page that might be printed before or after the file. If the file is sent to an e-mail destination, this description is the subject of the e-mail. You can specify up to 60 characters. If the text contains spaces or characters that the shell might interpret, enclose the text in single or double quotation marks. This option overrides the **title-text** job attribute. For information about the default value, see “title-text” on page 105.

Tip: Whether a title is printed on a separator pages depends on how the administrator has configured the separator page.

-w Writes a message to the terminal when the file is removed from the system spool for any reason. Some reasons are:

- The file has finished printing.
- The file has been transmitted to a LAN printer or to the z/OS UNIX sendmail function. You might receive notification before the file has finished printing or has been sent to the e-mail destination. You might receive notification even though a transmission error has occurred.
If your administrator has requested that Infoprint Server retain files on the system spool after transmission, you receive notification after the retention time expires.
- The operator has deleted the file.

Tip: Notification might be delayed to improve system performance.

Operand

filename

The path name of each file that you want to print or send to an e-mail destination. To specify data from standard input (keyboard data or the output from another command), omit the file name or specify a dash (–) as the file name. To print an MVS data set, specify **//** before the file name.

Rules:

1. If the data stream must be transformed to a different data format, you can submit only one file at a time with each **lp** command.
2. If you specify more than one file with the same **lp** command, all files must have the same data format. For example, all files must be PostScript files or text files.

Results

After Infoprint Server accepts the print job, the **lp** command returns an Infoprint Server job ID, which you can use to query and cancel the job. For example, you might receive a message such as:

AOP007I Job 14584 successfully spooled to myprinter.

The Infoprint Server job ID can help the system operator find your job on the JES spool. The job ID field of the data set that Infoprint Server allocates on the JES spool contains the Infoprint Server job ID.

The Infoprint Server job ID is different, however, from the z/OS job ID, which is a unique job ID that z/OS assigns to the data set. JES operator commands return the z/OS job ID.

Sending a file to an e-mail destination

With the **lp** command, you can send the file to an e-mail destination instead of to a printer. When you send a file to an e-mail destination, your administrator can specify the e-mail address list of the recipients in the printer definition for the e-mail destination in the Printer Inventory, or you can specify the address list in an alias file that your administrator defines to z/OS UNIX sendmail. For information, see “Specifying the e-mail address list in an alias file” on page 112.

The e-mail has these characteristics:

- The file is an e-mail attachment. The name of the attachment is the name specified in the **sysout-dataset-name** job attribute. If this attribute is not specified, the name of the attachment is the last 8 characters of the file name. A pound sign (#) is used in the file name instead of any character that the system does not allow in a file name on the JES spool. For example, a slash or a period is replaced with a pound sign.
The name of the attachment contains an extension that indicates the type of data in the file. For example, **txt** indicates text data and **pdf** indicates PDF data.
- The subject of the e-mail is the value specified in the **-t** option or in the **title-text** job attribute. If none is specified, the subject is the title specified in the Allocation section of the printer definition. If none is specified, the subject is the ID of the user who entered the **lp** command.
- The sender is the user ID of the user who entered the **lp** command.
- You can receive replies from the e-mail unless a firewall prevents the z/OS system from receiving replies from the sending system. To receive replies, use the z/OS UNIX **mail** or **mailx** command.

Examples

Print a file on the default printer

To submit the file **File1** to your default printer, enter:

```
lp File1
```

Print a file on a specified printer

To submit the file **File1** to the printer **fred**, enter:

```
lp -d fred File1
```

Print a file on an undefined LAN printer

You want to print the file **File1** on a LAN printer at a remote site. Your administrator has not defined this printer. You must specify:

- The name that your administrator has defined to represent all remote printers (for example, **remote**)
- The printer’s Internet Protocol (IP) address
- The remote print queue

Enter:

lp

```
lp -d remote -o "print-queue-name=text  
printer-ip-address=leo.boulder.ibm.com" File1
```

Print an MVS data set

To submit the MVS data set *hlq.FILE1.LISTPS* to your default printer, where *hlq* is your user ID, enter:

```
lp //FILE1.LISTPS
```

To submit the MVS data set *FILE2.LISTPS* to your default printer, enter:

```
lp "'FILE2.LISTPS'"
```

Print a multi-document job

To submit the files *File1* and *File2* to the default printer, enter:

```
lp File1 File2
```

Each file is spooled to the printer separately.

Print a file-reference document

A *file-reference document* is a list of similar printable files that are separated by spaces, tabs, or new lines. For example, the file *bills.list* contains a list of files, each containing one customer's monthly statement. It looks like this:

```
40009801.dec97  
40009802.dec97  
40009803.dec97  
40009804.dec97  
:  
:
```

To print all the files listed in *bills.list* on your default printer, enter:

```
lp -o document-type=file-reference bills.list
```

The files are concatenated and printed as a single file.

Transform and print a job

If your installation has installed Infoprint Server Transforms or another optional transform product, you can submit a job in a format different from the ones the printer accepts. For more information, see "Transform a file to AFP format?" on page 26 and "Transform a file from AFP format?" on page 27.

To print the PCL file *sample.pcl* on the AFP printer *printer1*, enter:

```
lp -d printer1 sample.pcl
```

If you want to specify options for a file that is being transformed to AFP, you must use the *filter-options* attribute with the **lp** command. For example, to print pages 3–10 of the PCL file *sample.pcl* on the AFP printer *printer1* as an overlay, enter:

```
lp -d printer1 -o "filter-options='-p 3-10 -t overlay'" sample.pcl
```

If you want to specify job attributes for a file that is being transformed from AFP, you do not use the *filter-options* attribute with the **lp** command. You only use *filter-options* to specify **-c** and **-i** options. For example, to print the AFP file *sample.afp* on the PCL printer *PCLPRT* and printing in duplex, enter:

```
lp -d PCLPRT -o 'duplex=yes' sample.afp
```

To print the AFP file *sample.afp* on the PCL printer *PCLPRT* using the transform class *US* and print in duplex, enter:

```
lp -d PCLPRT -o "filter-options='-c us' duplex=yes" sample.afp
```

Print multiple copies of each file

To print two copies of each file on the default printer, enter one of these:

```
lp -n 2 Title Contents Body1 Body2 Append
```

```
lp -o copies=2 Title Contents Body1 Body2 Append
```

This command prints two copies of `Title`, followed by two of `Contents`, and so forth for each file in the job.

Tip: VTAM-controlled printers and some IPP-enabled printers do not support printing more than one copy. In this case, only one copy prints. If the file is sent to an e-mail destination instead of to a printer, only one copy is sent.

Print a file on both sides of the paper

To print file `File1` on the default printer and to print it on both sides of the paper, enter:

```
lp -o duplex=yes File1
```

Specify the attributes files

To print file `File5` on the default printer and to specify the two attributes files `default.att` and `special.att`, enter:

```
lp -o "attributes=default.att attributes=special.att" File5
```

Suppose that the file `default.att` contains these lines:

```
input-tray=bottom
duplex=yes
output-bin=collator
```

The file `special.att` contains these lines:

```
input-tray=top
copies=5
title-text='Special Report'
```

The preceding command is equivalent to this command:

```
lp -o "input-tray=top duplex=yes output-bin=collator
copies=5 title-text='Special Report'" File5
```

The value of **input-tray** in `special.att` overrides the value in `default.att` because you specified `special.att` last.

Tip: These examples assume that the attributes files are in the current directory, or that you have set the **AOPPATH** environment variable to include the directories where the attributes files reside. If this is not the case, you would specify the attributes files by their absolute path names.

Override an attribute value in an attributes file

To print file `File1` on the default printer and override the value of **yes** for the **duplex** attribute specified in the `default.att` attributes file, enter:

```
lp -o "attributes=default.att duplex=tumble" File1
```

Specify the AOPOPTIONS environment variable

To set the **AOPOPTIONS** environment variable to your address, add a line like this one to your **.profile** file:

```
export AOPOPTIONS="address-text={'13 Division St.' 'Foxboro, MA 02035'}"
```

Until you reset the **AOPOPTIONS** environment variable, every **lp** command you enter includes this value. For example, this command:

lp

```
lp myfile.ps
```

is equivalent to:

```
lp -o "address-text={'13 Division St.' 'Foxboro, MA 02035'}" myfile.ps
```

Because the **lp** command reads the value of the **AOOPTIONS** environment variable before the options you specify on the command line, you can override the values of this variable. For example, if you want a single job delivered to a different address, enter:

```
lp -o "address-text={'999 Eclipse Alley' 'Pawtucket, RI 02860'}" myfile.ps
```

Request notification by message

To print file `File1` on the default printer and to receive a message when the file is printed, enter:

```
lp -w File1
```

Tip: If the printer is a LAN printer, the **lp** command writes a message when the file is transmitted to the printer. When you receive the message, the file might not actually have finished printing.

Submit and hold a job

To submit file `File1` to the default printer and to hold it so that it does not print until the operator releases it, enter:

```
lp -o hold=true File1
```

Specify a code page for ASCII files

To print the files `File1` and `File2` and to specify the code page `ISO8859-1`, enter:

```
lp -d Printer1 -o document-codepage=ISO8859-1 File1 File2
```

Print from standard input

You can use the **lp** command to print the output from other commands. For example, to print a list of all the files in the current directory, enter:

```
ls -la | lp
```

Paginate line data and print with a header on each page

If your administrator has specified the LPD compatibility filter (**lpd_compat.so**) for the printer in the Printer Inventory, you can specify filter options that are equivalent to the **FILTER**, **WIDTH**, and **LINECOUNT** options of the z/OS Communications Server (TCP/IP) LPR command. The LPD compatibility filter can be used with text and line data when you print on an AFP printer or a JES line printer. For a description of the options that the LPD compatibility filter supports, see “filter-options” on page 93.

To print data set `MYDATA`, which contains line data, on the AFP printer `afpprinter`, with a header on each page, a maximum width of 80 characters, and a maximum length of 60 lines, enter:

```
lp -d afpprinter -o "filter-options='-f p -w 80 -l 60'" '///MYDATA'
```

Send files to an e-mail destination

To send files `File1` and `File2` to the e-mail address list in printer definition `deptmail`, specify a subject for the e-mail, and specify a form definition that is used when the AFP data is converted to PDF format, enter:

```
lp -d deptmail -t "Monthly Report" -o "form-definition=F1MYDEF" File1 File2
```

This example assumes that the AFP to PDF transform is requested for AFP data in the printer definition named `deptmail`.

Results: The recipients listed in printer definition deptmail receive two e-mails:

- The sender of the e-mails is the user ID of the user who entered the **lp** command.
- File File1 is attached to one e-mail, while file File2 is attached to another e-mail. The name of the attachments are: FILE.pdf and FILE2.pdf. The files are in PDF format and can be viewed and printed with Adobe Acrobat Reader.
- The subject of both e-mails is Monthly Report.

Environment variables

The **lp** command uses these environment variables:

AOPCONF Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (**\$HOME/.aopconf**) and the system default configuration file (**/etc/Printsrv/aopd.conf**). For more information about the configuration file, see *z/OS Infoprint Server Customization*.

AOOPTIONS Specifies a string of attributes and values that the **lp** command includes before the values of the **-o** option.

AOPPATH Defines the directory path that the **lp** command searches for attributes files. The default is your current directory. If the directory where an attributes file resides is not included in the value of **AOPPATH**, you can specify the file by its absolute path name.

LPDEST Names the default printer. This variable takes precedence over **PRINTER**.

PRINTER Names the default printer if **LPDEST** is not defined.

NLSPATH Names the directory paths that the **lp** command searches for message catalogs.

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

Exit values

0 Infoprint Server accepted the request.

>0 An error occurred that prevented Infoprint Server from accepting the request. Some possible errors are:

- The command syntax is not valid.
- The selected printer cannot print the type of data in one of the files.
- The selected printer does not support one of the specified job attributes.
- Infoprint Server is not available.
- There was an error in reading the Infoprint Server configuration file.

lp

Portability

The **-m**, **-o**, **-s**, **-t**, and **-w** options are extensions to the POSIX.2 standard. There are no extensions to the XPG4.2 standard for the **lp** command.

lpstat—Show printer names and locations and status of print jobs

Format

```
lpstat [-dt] [-a [printername ...]] ... [-o [printername ...]] ...
      [-p [printername ...]] ... [-u [userid ...]] ... [jobid ...]
```

Description

lpstat writes printer definition names, location information specified in the printer definitions, and the status of jobs to standard output.

For printer definitions in the Infoprint Server Printer Inventory, the **lpstat** command returns this information:

- The name of the printer definition
- The number of jobs submitted to the printer definition using the Print Interface component of Infoprint Server
- The location information in the printer definition
- The description information in the printer definition

For jobs that were submitted through the Print Interface component of Infoprint Server, the **lpstat** command returns this information:

- The Infoprint Server job ID. The Infoprint Server job ID is a unique job ID assigned to each print job. You can use it to cancel the job with the **cancel** command.

The Infoprint Server job ID can help the system operator find your job on the JES spool. In most cases, the job ID field of data sets that Infoprint Server allocates on the JES spool contains the Infoprint Server job ID.

The Infoprint Server job ID is different, however, from the z/OS job ID, which is a unique job ID that z/OS assigns to the data set. JES operator commands return the z/OS job ID.

- The user ID of the person who submitted the job.
- The state of each file in the job:

pending The file is waiting to print.

processing The file has been placed on the JES spool and selected for processing. It might be:

- Being transmitted to a local area network (LAN) printer or to a print server
- Printing

held The file is held on the JES spool and cannot print for one of these reasons:

- The user specified **hold=true** when submitting the job.

Tip: JES3 does not recognize a job that is held for this reason and returns **pending**.

- The operator held the job.

completed The file has been processed successfully. It remains on the JES spool for one of these reasons:

lpstat

- Other files in the job are still being processed. The file will be removed from the spool after all files in the job have been processed.
- Your administrator has specified that files should be retained after transmission to a LAN printer or to a print server. The file will be removed from the spool when the retention period expires.

failed Processing has failed. The file remains on the JES spool for one of these reasons:

- Transmission to a LAN printer or to a print server has failed. Your administrator has specified that files should be retained after transmission. The file will be removed from the spool when the retention period expires.
- An error occurred during processing. The file is held.

purged The file was deleted before printing.

- The data format of the job specified in the **document-format** job attribute or determined by Infoprint Server.
- The number of bytes in each file in the job.
- The name of each file or file-reference document in the job.

For jobs submitted to the Print Interface subsystem, the filename is in this format:

job-name.job-id.dataset-name

job-name

The name of the z/OS job. The job name can help the system operator locate the data set on the JES spool.

job-id

The ID that z/OS assigned to the job. The job ID can help the system operator locate the data set on the JES spool.

dataset-name

The name of the data set specified in the DSNAMES parameter on the DD JCL statement for the data set. This name is the last qualifier of the fully qualified data set name on the JES spool. If the DSNAMES parameter was not specified, this field is blank.

When **lpstat** returns information about multiple jobs, the order is not significant. The first job listed might not be the next job to print.

Options

-a [*printername ...*]

Displays the names and locations of the specified printers. If you do not specify a printer name, this option displays the names and locations of all printers defined in the Printer Inventory.

If you specify more than one printer name in the **-a** option, enclose the entire value in quotation marks. Or, you can repeat the **-a** option.

-d Displays the name and location of the default printer that the administrator has defined. If there is no default printer, **lpstat** returns an error message.

Tip: This option does not display the name or location of a default printer that you defined with the LPDEST or PRINTER environment variable. To display the values of these variables, use the z/OS UNIX **echo** command.

-o [printername ...]

Displays information about the specified printers and all jobs that you submitted to the specified printers. If you do not specify a printer name, this option displays information about printers defined in the Printer Inventory and all jobs you submitted to them through the Print Interface component of Infoprint Server.

If you specify more than one printer name in the **-o** option, enclose the entire value in quotation marks. Or, you can repeat the **-o** option.

-p [printername ...]

Displays the names and locations of the specified printers. If you do not specify a printer name, this option displays the names and locations of all printers defined in the Printer Inventory.

If you specify more than one printer name in the **-p** option, enclose the entire value in quotation marks. Or, you can repeat the **-p** option.

-t

Displays information about all printers defined in the Printer Inventory and all jobs submitted to them through the Print Interface component of Infoprint Server.

-u [userid ...]

Displays information about all jobs that the specified users submitted to any printer. If you specify **-u** without a user name, this option displays information about all jobs that all users submitted to any printer. If you do not specify **-u**, **lpstat** displays information about all jobs that you submitted to any printer.

The user ID is case-sensitive. Use the exact uppercase and lowercase characters.

If you specify more than one user name in the **-u** option, enclose the entire value in quotation marks. Or, you can repeat the **-u** option.

Operand

jobid ...

Identifies the job you want to display information about. Specify the Infoprint Server job ID, not the z/OS job ID.

The **lp** command and AOPPRINT JCL procedure return the Infoprint Server job ID when a job is accepted for printing. Infoprint Server also can return the Infoprint Server job ID to you when you submit a job from a remote system.

Examples

Display the names and locations of all printers

To display the names of all printer definitions in the Infoprint Server Printer Inventory and the location information in the printer definition, enter:

```
lpstat -a
```

Display the name and location of the default printer

To display the name and location of the default printer, enter:

```
lpstat -d
```

Display information about selected jobs

To display the status of the jobs whose Infoprint Server job IDs are 14 and 16, enter:

lpstat

```
lpstat 14 16
```

Display information about all jobs that you submitted

To display the status of all the jobs that you submitted to any printer definition, enter:

```
lpstat
```

Display information about all jobs submitted by a user

To display the status of all jobs that user MARTHA submitted to any printer definition, enter:

```
lpstat -u MARTHA
```

Display information about a printer and all jobs that you submitted to it

To display the location of printer Printer1 and the status of all jobs that you submitted to it, enter:

```
lpstat -o Printer1
```

Display information about several printers and all jobs that you submitted to it

To display the location of printers Printer1 and Printer2 and the status of all jobs that you submitted to them, enter:

```
lpstat -o "Printer1 Printer2"
```

Display information about all printers and all jobs

To display the status of all printers and all jobs that have been submitted by all users in the system, enter:

```
lpstat -t
```

Environment variables

The **lpstat** command uses these environment variables:

AOPCONF Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (**\$HOME/.aopconf**) and the system default configuration file (**/etc/Printsrv/aopd.conf**). For more information about the configuration file, see *z/OS Infoprint Server Customization*.

NLSPATH Names the directory paths that the **lpstat** command searches for message catalogs.

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

Exit values

0 Infoprint Server accepted the request.

- >0 An error occurred that prevented Infoprint Server from accepting the request. Some possible errors are:
- The command syntax is not valid.
 - Infoprint Server is not available.
 - There was an error in reading the Infoprint Server configuration file.

Portability

There are no extensions to any Portable Operating System Interface for Computer Environments (POSIX) standard or to the XPG4.2 standard for the **lpstat** command.

pcl2afp—Transform PCL data to AFP data

Format

```
pcl2afp [-a imagetype] [-c transformclass] [-o outputfile]
        [-p pagerange] ... [-t outputtype] [inputfile ...]
```

Description

The **pcl2afp** command transforms a Printer Control Language (PCL) 5 or 5e data stream file into an Advanced Function Presentation (AFP) data stream file. This command is part of the Infoprint Server Transforms product.

If you specify multiple values of the same option, **pcl2afp** uses the last value that you specified, with the exception of the **-p** option. Up to 20 values of the **-p** option accumulate.

When using the **pcl2afp** command, you can specify one or more input files to be transformed. If you do not specify an input file name, or if you specify a dash (-) as the file name, **pcl2afp** uses standard input. The output file name is also optional. If you do not specify one, the **pcl2afp** command writes the results to standard output.

Options

Tip: You can use the **filter-options** job attribute with the **lp** command to pass any of these options except **-o *outputfile*** to the AFP to PCL transform.

-a *imagetype*

Determines the type of AFP data stream image to generate for each page in the PCL file.

Values are:

io1-g4 Compressed Image Object Content Architecture (IOCA) image in Modified Telecommunication Standardization Sector (TSS) T.6 G4 Facsimile Coding Scheme (G4 MMR) format. This is the recommended output type because it takes up less space on the hard disk, and it prints faster.

Tips:

1. Some older AFP printers do not support printing with an image type of **io1-g4**. For these printers, specify an image type of **io1-mmr** because it is the compressed image type that they support. This image type results in faster printing than uncompressed image types.
2. TSS was formerly the International Telegraph and Telephone Consultative Committee (CCITT).

im1 IM1 image. This type of image is not compressed.

io1 IOCA image. This type of image is not compressed.

io1-mmr

Compressed IOCA image in Modified Modified Read (MMR) format.

-c *transformclass*

Specifies the name of a transform class that your administrator has defined. The transform class determines these options:

- The length and width of the generated image
- The page margins
- The resolution of the output image
- The amount of memory that the transform allocates

Ask your administrator for the name of a transform class suitable for the printer and the type of job.

Tip: If the transform class specifies a resolution that the printer does not support, PSF prints the image under most conditions, but with degraded results.

-o *outputfile*

Specifies the output path and file into which the transform output (that is, AFP data) is written. The transform overwrites any existing data in the output file. If you do not specify an output file, the result is written to standard output (STDOUT). If you specify more than one output file, the last path and file name are used.

To specify an MVS data set, such as a sequential or partitioned data set, precede the data set name with `//`. When you specify a fully qualified name, two sets of quotation marks are required. For example, `"/'/hlq.PDS(MYDOC)'"` or `"/'/hlq.SEQDS'"`. When you specify a partially qualified name, you only need one set of quotation marks. For example, `"/'PDS(MYDOC)'"` or `"/'SEQDS'"`.

If you specify an MVS data set, allocate and catalog the data set before you run this command. Allocate a data set that is large enough to hold the output data stream. The size of the output data stream depends on the complexity of the document and the type of image compression you select in the **-a** option. Typically, an output AFP data stream is several times as large as the input data stream. Allocate the output data set with these characteristics:

- Record format: VBM
- Record length: 8K (8192) bytes or larger

-p *pagerange*

Specifies that the output should contain only selected pages. Up to 20 values of the **-p** option accumulate.

The **-p** option counts pages by their actual sequence in the document, not by page number. For example, to write only the last page of a document whose pages are numbered i, ii, 1, 2, 3, 4, specify **-p 6**.

Examples of values include:

- p even** Write even pages.
- p odd** Write odd pages.
- p 1-10** Write the first through tenth pages.
- p 10-** Write pages from the tenth page until the end of the file.
- p 1 -p 3 -p 6** Write the first, third, and sixth pages.

-t *outputtype*

Determines the type of output to generate.

Values are:

pcl2afp

document

Printable document.

overlay

Graphic image that can be printed on each page of a printable document.

pagesegment

Graphic image that can be embedded in a printable document.

Tip: When generating overlays or page segments from multiple-page documents, you might want to use the **-p** option to select pages. Otherwise, one overlay or page segment is created for each page of the input file.

Operand

inputfile

Specifies an input file to be transformed. If you specify more than one input file name, the **pcl2afp** command concatenates the files. The results are written to a single output file (if one is specified) or to standard output.

In addition, you can specify PCL inline resource files as input files to the **pcl2afp** command. The file name of the inline resource file must precede the file name of the PCL printable file so that **pcl2afp** concatenates the files in the correct order.

If you do not specify an input file, or if you specify a dash (-) as the file name, **pcl2afp** uses standard input.

Limitations

- The PCL to AFP transform produces monochrome output.
- PCL data can contain device commands (for example, to begin or end duplexing or to change the input bin). Because the AFP architecture defines those device functions in a form definition resource, the **pcl2afp** command ignores the device commands in the print data. To access those device functions, you must specify them in the form definition or attributes file, or on the print command.
- Resolution conversion algorithms might produce a degraded appearance when used to reduce the resolution of a data stream. For this reason, **pcl2afp** might degrade the appearance of higher-resolution data streams when used with 240-pel printers. You should verify that print fidelity is satisfactory.
- There are subtle differences between PCL4 and PCL5e when it comes to handling fonts. While many PCL4 files work with **pcl2afp**, some might not produce the expected output.

Examples

Transform a file, specifying transform class

To transform the PCL file `myfile.pcl` into an AFP data stream, using the `a4_300` transform class, and write the result to a file called `myfile.afp`, enter:

```
pcl2afp -c a4_300 -o myfile.afp myfile.pcl
```

Transform and print a file, specifying image type

To transform the PCL file `myfile.pcl` into an AFP data stream as an IO1-MMR image, and send the result to the default printer with the **lp** command, enter:

```
pcl2afp -a io1-mmrc myfile.pcl | lp
```


Transform a file using redirection

To transform the PCL file `input.pcl` into the AFP output file called `output.afp`, enter:

```
pcl2afp <input.pcl> output.afp
```

Note: You can use redirection operators only with UNIX files.

Transform multiple files and concatenate the output

To transform the PCL files `input.01.pcl`, `input.02.pcl`, ... `input.xx.pcl` into one AFP output file called `output.afp`, enter:

```
pcl2afp -o output.afp input.01.pcl input.02.pcl ... input.xx.pcl
```

Transform a UNIX file to an MVS data set

To transform file `input.pcl` into an existing, cataloged MVS output data set called `hlq.OUTPUT.AFP(member)`, where `hlq` is your user ID, enter:

```
pcl2afp -o "'/hlq.OUTPUT.AFP(member)'" input.pcl
```

Transform an MVS data set, writing the output to a UNIX file

To transform the MVS data set `hlq.INPUT.PCL(member)`, where `hlq` is your user ID, into an output file called `output.afp`, enter:

```
pcl2afp -o output.afp "'/hlq.INPUT.PCL(member)'"
```

Environment variables

The **pcl2afp** command uses these environment variables:

AOPCONF	Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (\$HOME/.aopconf) and the system default configuration file (/etc/Printsrv/aopd.conf). For more information about the configuration file, see <i>z/OS Infoprint Server Customization</i> .
NLSPATH	Names the directory paths that the pcl2afp command searches for message catalogs.

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

For the format of the configuration files, see *z/OS Infoprint Server Customization*.

Exit values

0	The data was transformed successfully.
>0	An error occurred.

pdf2afp and ps2afp—Transform PDF or PostScript data to AFP data

Format

```
pdf2afp [-a imagetype] [-c transformclass] [-l length] [-o outputfile]
        [-p pagerange] ... [-r resolution] [-t outputtype] [-w width]
        [-x xmargin] [-y ymargin] [inputfile...]

ps2afp [-a imagetype] [-c transformclass] [-g pagerange] ...
        [-i initializationfile...] [-l length] [-o outputfile] [-p pagerange] ...
        [-r resolution] [-t outputtype] [-w width] [-x xmargin] [-y ymargin]
        [inputfile...]
```

Description

The **ps2afp** command and its alias, the **pdf2afp** command, convert a PostScript or Portable Document Format (PDF) data stream file into an Advanced Function Presentation (AFP) data stream file. These commands are part of the Infoprint Server Transforms product.

If the Kanji AFP Print feature of Infoprint Server Transforms is installed, you can transform Japanese PostScript and PDF documents to AFP format. The **pdf2afp** and **ps2afp** commands map a variety of DBCS fonts to the Heisei Kaku Gothic or Heisei Mincho font.

If you specify multiple values of the same option, **ps2afp** uses the last value, with the exception of the **-g** and **-p** options. Up to 20 values of the **-p** option, or any number of values of the **-g** option, accumulate.

You can specify one or more input files to be transformed. If you do not specify an input file name, or if you specify a dash (-) as the file name, **ps2afp** reads standard input. The output file name is also optional. If you do not specify one, the **ps2afp** command writes the results to standard output.

Options

Tip: You can use the **filter-options** job attribute with, for example, the **lp** command to pass any of these options except **-o outputfile** to the PostScript or PDF to AFP transform.

-a imagetype

Determines the type of AFP data stream image to generate for each page in the PostScript or PDF file.

Values are:

io1-g4 Compressed Image Object Content Architecture (IOCA) image in Modified Telecommunication Standardization Sector (TSS) T.6 G4 Facsimile Coding Scheme (G4 MMR) format. This is the recommended output type because it takes up less space on the hard disk, and it prints faster.

Tips:

1. Some older AFP printers do not support printing with an image type of **io1-g4**. For these printers, specify an image type of **io1-mm** because it is the compressed image type that these printers support. This image type results in faster printing than uncompressed image types.
2. TSS was formerly the International Telegraph and Telephone Consultative Committee (CCITT).

im1 IM1 image. This type of image is not compressed.

io1 IOCA image. This type of image is not compressed.

io1-mm

Compressed IOCA image in Modified Modified Read (MMR) format.

-c transformclass

Specifies the name of a transform class that your administrator has defined. The transform class determines these options:

- The initial transform configuration
- The fonts used in the transformed files

Ask your administrator for the name of a transform class suitable for the type of job.

-g pagerange

Specifies that the output should contain only selected pages. Any number of values of the **-g** option accumulate. The **-g** option can be used only for PostScript documents that conform to the Data Stream Compatibility (DSC) standard. It is not valid for PDF documents.

The difference between the **-g** and **-p** options is that **-g** identifies pages by the label specified with the PostScript **%%Page** command (usually a page number), while **-p** counts them by their actual sequence in the document. For example, to write only the last page of a document whose pages are numbered i, ii, 1, 2, 3, 4, specify **-g 4** or **-p 6**.

Tip: Unlike the **-p** option, the **-g** option does not support the **even** and **odd** keywords.

Examples of values include:

```
-g iii-vi      Write pages iii through vi.
-g 1-10       Write pages 1 through 10.
-g 10-        Write pages from page 10 until the end of the job.
-g 1 -g 3 -g 6
               Write pages 1, 3, and 6.
-g 3-1 3-28   Write pages 3-1 through 3-28.
```

-i initializationfile

Specifies one or more ASCII PostScript files that are added to the start of the job to set up and initialize the PostScript transform. If you specify more than one file, they are processed in the order that you specify them. The **-i** option is not valid for PDF documents.

-l length

Specifies the length of the generated image. In general, specify the length

of the physical page. For more information about this option, see “Usage notes” on page 76. Specify a number followed by one of these units:

in Inches
mm Millimeters
pel Pels, the default unit

Inch values and millimeter values can contain a decimal point. Pel values cannot.

Values are:

<u>11i</u>	11 inches, the default for all printers
0.1334in to 53in	Inch values for 240-pel printers
0.1067in to 53in	Inch values for 300-pel printers
0.0667in to 53in	Inch values for 480-pel printers
0.0534in to 53in	Inch values for 600-pel printers
3.3867mm to 1346.2mm	Millimeter values for 240-pel printers
2.7094mm to 1346.2mm	Millimeter values for 300-pel printers
1.6934mm to 1346.2mm	Millimeter values for 480-pel printers
1.3547mm to 1346.2mm	Millimeter values for 600-pel printers
32pel to 12720pel	Pel values for 240-pel printers
32pel to 15900pel	Pel values for 300-pel printers
32pel to 25440pel	Pel values for 480-pel printers
32pel to 31800pel	Pel values for 600-pel printers

Examples of values include:

```
-l 40mm
-l 200.5mm
-l 13in
-l 5280
-l 5280pel
```

Tip: If a text margin is already built into the file, try **-l 11in** to set the length to 11 inches.

-o *outputfile*

Specifies the output path and file into which the transform output (that is, AFP data) is written. The transform overwrites any existing data in the output file. If you specify more than one output file, the last path and file name are used. If you do not specify an output file, the result is written to standard output (STDOUT).

To specify an MVS data set, such as a sequential or partitioned data set, precede the data set name with **//**. When you specify a fully qualified name, two sets of quotation marks are required. For example, `"/'/hlq.PDS(MYDOC)'"` or `"/'/hlq.SEQDS'"`. When you specify a partially qualified name, you only need one set of quotation marks. For example, `"/PDS(MYDOC)"` or `"/SEQDS"`.

If you specify an MVS data set, allocate and catalog the data set before you run this command. Allocate a data set that is large enough to hold the

output data stream. The size of the output data stream depends on the complexity of the document and the type of image compression you select in the **-a** option. Typically, an output AFP data stream is several times as large as the input data stream. Allocate the output data set with these characteristics:

- Record format: VBM
- Record length: 8K (8192) bytes or larger

-p *pagerange*

Specifies that the output should contain only selected pages. Up to 20 values of the **-p** options accumulate.

The difference between the **-p** and **-g** options is that **-p** counts pages by their actual sequence in the document, while **-g** identifies them by page label. For example, to write only the last page of a document whose pages are numbered i, ii, 1, 2, 3, 4, specify **-p 6** or **-g 4**.

Examples of values include:

- p even** Write even pages.
- p odd** Write odd pages.
- p 1-10** Write the first through tenth pages.
- p 10-** Write pages from the tenth page until the end of the job.
- p 1 -p 3 -p 6** Write the first, third, and sixth pages.

-r *resolution*

Specifies the resolution of the output image. Select the correct resolution for the printer on which you intend to print the image.

Values are:

- 240** 240 pels per inch (for example, IBM 3812, 3825, 3827, 3835, and 3900 printers)
- 300** 300 pels per inch (for example, IBM 4019, 4028, 4029, and 4039 printers and some Hewlett-Packard printers)
- 480** 480 pels per inch
- 600** 600 pels per inch (for example, IBM Infoprint 60 and Infoprint 4000 printers), the default

Tip: If you specify a resolution that the printer does not support, PSF prints the image under most conditions, but with degraded results.

-t *outputtype*

Determines the type of output to generate.

Values are:

document

Printable document.

overlay

Graphic image that can be printed on each page of a printable document.

pagesegment

Graphic image that can be embedded in a printable document.

Tip: When generating overlays or page segments from multiple-page documents, you might want to use the **-g** or **-p** option to select pages. Otherwise, one overlay or page segment is created for each page of the input file.

-w *width*

Specifies the maximum width of the generated image. In general, specify the width of the physical page. For more information about this option, see “Usage notes” on page 76. Specify a number followed by one of these units:

in Inches
mm Millimeters
pel Pels, the default unit

Inch values and millimeter values can contain a decimal point. Pel values cannot.

Values are:

<u>8.5in</u>	8.5 inches, the default for all printers
0.1334in to 25.5in	Inch values for 240-pel printers
0.1067in to 25.5in	Inch values for 300-pel printers
0.0667in to 25.5in	Inch values for 480-pel printers
0.0534in to 25.5in	Inch values for 600-pel printers
3.3867mm to 647.7mm	Millimeter values for 240-pel printers
2.7094mm to 647.7mm	Millimeter values for 300-pel printers
1.6934mm to 647.7mm	Millimeter values for 480-pel printers
1.3547mm to 647.7mm	Millimeter values for 600-pel printers
32pel to 6120pel	Pel values for 240-pel printers
32pel to 7650pel	Pel values for 300-pel printers
32pel to 12240pel	Pel values for 480-pel printers
32pel to 15pel	Pel values for 600-pel printers

Examples of values include:

```
-w 40mm
-w 200.5mm
-w 13in
-w 4000
-w 4000pel
```

Tip: If a text margin is already built into the file, try **-w 8.5in** to set the width to 8.5 inches.

-x *xmargin*

Specifies a horizontal margin or border around the generated image to avoid the non-printable areas of some printers. For more information about this option, see “Usage notes” on page 76. Specify a number followed by one of these units:

in Inches

mm Millimeters

pel Pels, the default unit

Inch values and millimeter values can contain a decimal point. Pel values cannot.

Values are:

0 Zero, the default for all printers

0in to 12.75in Inch values for all printers

0mm to 323.85mm
Millimeter values for all printers

0pel to 3060pel
Pel values for 240-pel printers

0pel to 3825pel
Pel values for 300-pel printers

0pel to 6120pel
Pel values for 480-pel printers

0pel to 7650pel
Pel values for 600-pel printers

Tips:

1. Because the X value specifies margins on *both* the left and right sides of the page, the X value can be no more than half of the width (**-w**) of the generated image. For example, if you specify a width of 8 inches, the X value can be no larger than 4 inches. If you specify an X value of 5 inches, a blank page is printed because the sum of the left and right margins exceeds the width of the paper.
2. The X value does not shift the image on the page. The image is clipped if it is defined to print in the left or right margin.

-y *ymargin*

Specifies a vertical margin or border around the generated image to avoid the non-printable areas of some printers. For more information about this option, see "Usage notes" on page 76. Specify a number followed by one of these units:

in Inches

mm Millimeters

pel Pels, the default unit

Inch values and millimeter values can contain a decimal point. Pel values cannot.

Values are:

0 Zero, the default for all printers

0in to 26.5in Inch values for all printers

0mm to 673.1mm
Millimeter values for all printers

0pel to 6360pel
Pel values for 240-pel printers

pdf2afp, ps2afp

0pel to 7950pel

Pel values for 300-pel printers

0pel to 12720pel

Pel values for 480-pel printers

0pel to 15900pel

Pel values for 600-pel printers

Tips:

1. Because the Y value specifies margins on *both* the top and bottom of the page, the Y value can be no more than half of the length (-l) of the generated image. For example, if you specify a length of 12 inches, the Y value can be no larger than 6 inches. If you specify a Y value of 7 inches, a blank page is printed because the sum of the top and bottom margins exceeds the length of the paper.
2. The Y value does not shift the image on the page. The image is clipped if it is defined to print in the top or bottom margin.

Operand

inputfile

Specifies an input file to be transformed. If you specify more than one input file name, the **ps2afp** command concatenates the files. The results are written to a single output file (if one is specified) or to standard output.

In addition, you can specify PostScript inline resource files as input files to the **ps2afp** command. The file name of the inline resource file must precede the file name of the PostScript or PDF print file so that **ps2afp** concatenates the files in the correct order.

If you do not specify an input file, or if you specify a dash (-) as the file name, **ps2afp** uses standard input.

Usage notes

- The PostScript or PDF file might contain the commands **letter** and **legal**. If these commands are present in the PostScript or PDF file, the size of the transformed image might not be what you expect. The **letter** and **legal** commands override the length and width values specified for the transform.
- If the **letter** and **legal** commands are not used, the position of PostScript or PDF data on the page depends on the interaction of the length and width values specified for the transform with the form definition you use. In general, to position data on the page:
 - Use **-l** and **-w** to set the physical page dimensions.
 - Use a form definition that specifies zero vertical offset and zero horizontal offset or specify X and Y offsets of 0 when you submit the print job.
- Use **-x** and **-y** to avoid any areas that your printer cannot print. These options do not shift the image on the page. If the image is defined to print in the unprintable areas, it is clipped.

Limitations

- The Postscript to AFP and PDF to AFP transform produces monochrome output.
- PostScript data can contain device commands (for example, to begin or end duplexing or to change the input bin). Because the AFP architecture defines those device functions in a form definition resource, the **ps2afp** command

ignores the device commands in the print data. To access those device functions, you must specify them in the form definition or attributes file, or on a print command, when you print the job.

- Resolution conversion algorithms might produce a degraded appearance when used to reduce the resolution of images imbedded in a data stream. For this reason, **ps2afp** might degrade the appearance of higher-resolution images when used with 240-pel printers. You should verify that print fidelity is satisfactory.
- This transform *cannot* create the AFP FS45 image type, which the IBM Infoprint Color 130 Plus printer requires. However, the PostScript to AFP and PDF to AFP transform available with Infoprint Manager for AIX can create the FS45 image type. If your installation has installed Infoprint Manager for AIX, your administrator can set up the printer definition for the IBM Infoprint Color 130 Plus printer to run the PostScript to AFP and PDF to AFP transform on Infoprint Manager for AIX.

Examples

Transform a job, specifying image size

To transform the PostScript file `myfile2.ps` into an AFP data stream, with an image that is 8 inches high and 5 inches wide, and write the result to a file called `myfile2.afp`, enter:

```
ps2afp -l 8in -w 5in -o myfile2.afp myfile2.ps
```

Transform and print a job, specifying resolution

To transform the PDF file `myfile1.pdf` into an AFP data stream, and then submit it to the 4019 printer called `robin`, enter:

```
pdf2afp -r myfile1.pdf | lp -d robin
```

Tip: You need to specify a resolution of pels (`-r`) because the 4019 is a -pel resolution printer. The default resolution for the **pdf2afp** command is 600 pels.

Transform a job, specifying transform class

To transform the PostScript file `myfile.ps` into an AFP data stream, using the `bigjob` transform class, and write the result to a file called `myfile.afp`, enter:

```
ps2afp -c bigjob -o myfile.afp myfile.ps
```

Transform a job, using redirection

To transform the PostScript file `input.ps` into the AFP output file called `output.afp`, enter:

```
ps2afp <input.ps> output.afp
```

Note: You can only use redirection operators with z/OS UNIX files.

Transform multiple files and concatenate the output

To transform the PostScript files `input.01.ps`, `input.02.ps`, ... `input.xx.ps` into one AFP output file called `output.afp`, enter:

```
ps2afp -o output.afp input.01.ps input.02.ps ... input.xx.ps
```

Transform a UNIX file to an MVS data set

To transform file `input.ps` into an existing, cataloged MVS output data set called `hlq.OUTPUT.AFP(member)`, where `hlq` is your user ID, enter:

```
ps2afp -o "'/hlq.OUTPUT.AFP(member)'" input.ps
```

Transform and print a job, specifying image type and resolution

To transform the PDF `myfile1.pdf` file into an AFP data stream in -pel resolution, as an IO1-MMR image, and send the result to the default printer with the `lp` command, enter:

pdf2afp, ps2afp

```
pdf2afp -a iol-mmrc -r myfile1.pdf | lp
```

Transform and print a job, specifying image type

To transform the PDF `myfile1.pdf` file into an AFP data stream as an IO1-MMR image, and send the result to the default printer with the **lp** command, enter:

```
pdf2afp -a iol-mmrc myfile1.pdf | lp
```

Transform an MVS data set, writing the output to a UNIX file

To transform the MVS data set `hlq.INPUT.PDF(member)`, where `hlq` is your user ID, into an output file called `output.afp`, enter:

```
pdf2afp -o output.afp "'hlq.INPUT.PDF(member)'"
```

Environment variables

The **pdf2afp** and **ps2afp** commands use these environment variables:

- | | |
|----------------|--|
| AOPCONF | Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (\$HOME/.aopconf) and the system default configuration file (/etc/Printsrv/aopd.conf). For more information about the configuration file, see <i>z/OS Infoprint Server Customization</i> . |
| NLSPATH | Names the directory paths that the pdf2afp command and the ps2afp command search for message catalogs. |

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

For the format of the configuration files, see *z/OS Infoprint Server Customization*.

Exit values

- | | |
|--------------|--|
| 0 | The data was transformed successfully. |
| >0 | An error occurred. |

sap2afp—Transform SAP OTF or ABAP data to AFP data

Format

```
sap2afp [-st] [-o outputfile] [-p pagerange] ... [-r resolution]
[inputfile ...]
```

Description

The **sap2afp** command transforms SAP R/3 Release 4.6C (as well as lower SAP R/3 releases) Output Text Format (OTF) and Advanced Business Application Programming (ABAP) data stream files:

- SAP OTF data streams are transformed into Advanced Function Presentation (AFP) Presentation Text Object Content Architecture (PTOCA) data streams.
- SAP ABAP data streams are transformed into line data streams.

This command is part of the Infoprint Server Transforms product.

If you specify multiple values of the same option, **sap2afp** uses the last value, with the exception of the **-p** option. Up to 20 values of the **-p** option accumulate.

You can specify one or more input files to be transformed. If you do not specify an input file name, or if you specify a dash (-) as the file name, **sap2afp** uses standard input. The output file name is also optional. If you do not specify one, the **sap2afp** command writes the results to standard output.

Tip: The size of the transformed image and the position of SAP data on the page depend on the values that the administrator has defined.

Options

Tip: You can use the **filter-options** job attribute with, for example, the **lp** command to pass any of these options except **-o *outputfile*** to the SAP to AFP transform.

-o *outputfile*

Specifies the output path and file into which the transform output (that is, AFP or line data) is written. The transform overwrites any existing data in the output file. If you specify more than one output file, the last specified path and file name are used. If you do not specify an output file, the result is written to standard output (STDOUT).

To specify an MVS data set, such as a sequential or partitioned data set, precede the data set name with **//**. When you specify a fully qualified name, two sets of quotation marks are required. For example, `"/'/hlq.PDS(MYDOC)'"` or `"/'/hlq.SEQDS'"`. When you specify a partially qualified name, you only need one set of quotation marks. For example, `"/'/PDS(MYDOC)'"` or `"/'/SEQDS'"`.

If you specify an MVS data set, allocate and catalog the data set before you run this command. Allocate a data set that is large enough to hold the output data stream. The size of the output data stream depends on the complexity of the document. Typically, an output AFP data stream is several times as large as the input data stream. Allocate the output data set with these characteristics:

- Record format: VBM
- Record length: 8K (8192) bytes or larger

sap2afp

-p *pagerange*

Specifies that the output should contain only selected pages. Up to 20 values of the **-p** option accumulate.

The **-p** option counts pages by their actual sequence in the document, not by page number. For example, to write only the last page of a document whose pages are numbered i, ii, 1, 2, 3, 4, specify **-p 6**.

Examples of values include:

- p even** Write even pages.
- p odd** Write odd pages.
- p 1-10** Write the first through tenth pages.
- p 10-** Write pages from the tenth page until the end of the job.
- p 1 -p 3 -p 6** Write the first, third, and sixth pages.

-r *resolution*

Specifies the resolution used to print image data in the job. Select the correct resolution for the printer on which you intend to print the job.

Values are:

- 240** 240 pels per inch (for example, IBM 3812, 3825, 3827, 3835, and 3900 printers)
- 300** 300 pels per inch (for example, IBM 3112, 3116, 4019, 4028, 4029, and 4039 printers and Hewlett-Packard printers)
- 480** 480 pels per inch
- 600** 600 pels per inch (for example, the IBM Infoprint 60 and Infoprint 4000 printers)

The default resolution is the resolution defined by the administrator. If the resolution has not been set, the transform fails with error message AOP2009E.

Tip: If you specify a resolution that the printer does not support, PSF prints the image data under most conditions, but with degraded results.

- s** Suppresses Graphic Object Content Architecture (GOCA) boxes. Some older printers do not print these boxes.
- t** Requests a trace. Specify this option only if instructed by IBM service personnel. For information about this option, see *z/OS Infoprint Server Messages and Diagnosis*.

Operand

inputfile

Specifies an input file to be transformed. If you specify more than one input file name, the **sap2afp** command concatenates the files. The results are written to a single output file (if one is specified) or to standard output.

If you do not specify an input file, or if you specify a dash (-) as the file name, **sap2afp** uses standard input.

Customization

You can customize the **sap2afp** transform by modifying these configuration files:

barcode.tab

Maps SAP OTF bar code names to the bar codes in Bar Code Object Content Architecture (BCOCA).

defcp.tab

Maps the Open Systems EBCDIC 1047 code page to the code page associated with the ABAP coded fonts specified in **pagedef.tab**.

fonts.tab

Maps the fonts used in the OTF data stream to AFP fonts.

image.tab

Defines values used to print image data.

pagedef.tab

Specifies the page definition, form definition, ABAP coded fonts, and the value of the OTF print option **PJPAPER**.

xxxx0000.tab

Maps a SAP code page to an AFP code page.

See your administrator for help with any file that you need to change. Note that even if you change only one configuration file, you must do these steps for **sap2afp** to find the configuration files:

- Copy all the configuration files into the same directory.
- Change the **AOP_SAP2AFP_RESOURCES** environment variable to point to that directory.

Limitations

The SAP to AFP transform produces monochrome output.

Examples

Transform a job, specifying resolution

To transform the SAP ABAP file `myfile.abap` for printing on a 600-pel AFP printer, and write the result to a file called `myfile.afp`, enter:

```
sap2afp -r 600 -o myfile.afp myfile.abap
```

Transform and print a job

To transform the SAP OTF file `myfile.otf` into an AFP data stream, and send the result to the default printer with the **lp** command, enter:

```
sap2afp myfile.otf | lp
```

Transform a job using redirection

To transform the SAP file `input.sap` into the AFP output file called `output.afp`, enter:

```
sap2afp <input.sap> output.afp
```

Note: You can use redirection operators only with UNIX files.

Transform multiple files and concatenate the output

To transform the SAP files `input.01.sap`, `input.02.sap`, ... `input.xx.sap` into one AFP output file called `output.afp`, enter:

```
sap2afp -o output.afp input.01.sap input.02.sap ... input.xx.sap
```

Transform a UNIX file to an MVS data set

To transform file `input.sap` into an existing, cataloged MVS output data set called `hlq.OUTPUT.AFP(member)`, where *hlq* is your user ID, enter:

sap2afp

```
sap2afp -o "'hlg.OUTPUT.AFP(member)'" input.sap
```

Transform an MVS data set, writing the output to a UNIX file

To transform the MVS data set *hlg.INPUT.SAP(member)*, where *hlg* is your user ID, into an output file called *output.afp*, enter:

```
sap2afp -o output.afp "'hlg.INPUT.SAP(member)'"
```

Environment variables

The **sap2afp** command uses these environment variables:

AOP_SAP2AFP_RESOURCES

Specifies the directory that contains resources for the **sap2afp** transform. The default value is **/usr/lpp/Printsrv/sap2afp**.

AOPCONF

Names the Infoprint Server configuration file. This variable takes precedence over the user-specific configuration file (**\$HOME/.aopconf**) and the system default configuration file (**/etc/Printsrv/aopd.conf**). For more information about the configuration file, see *z/OS Infoprint Server Customization*.

NLSPATH

Names the directory paths that the **sap2afp** command searches for message catalogs.

For information about setting and using environment variables, see *z/OS UNIX System Services User's Guide*.

Files

\$HOME/.aopconf

Contains the user-specific Infoprint Server configuration file. This file takes precedence over **/etc/Printsrv/aopd.conf**.

/etc/Printsrv/aopd.conf

Contains the system default Infoprint Server configuration file.

barcode.tab, defcp.tab, fonts.tab, image.tab, pagedef.tab, xxxx0000.tab

Customization files for the **sap2afp** transform.

Exit values

- 0** The data was transformed successfully.
- >0** An error occurred.

xml2afp—Transform XML to AFP data

The optional Infoprint XML Extender for z/OS (5655-J66) lets you transform Extensible Markup Language (XML) files to AFP format for printing or viewing. Using XML Extender with Infoprint Server, you can:

- Transform XML data to the AFP data format without printing the AFP data. To do this, use **xml2afp**. For information about **xml2afp**, see *Infoprint XML Extender for z/OS*.
- Print XML data on an IBM AFP printer. Infoprint Server automatically transforms the XML data to AFP format if your administrator has specified the XML to AFP transform in the printer definition for the AFP printer in the Printer Inventory.
- Print XML files on a non-AFP printer, such as a PCL printer. You can use this process:
 1. Transform XML data to the AFP data format without printing the AFP data. To do this, use **xml2afp**.
 2. Print the AFP data on a non-AFP printer. To do this, use the **lp** command or AOPPRINT JCL procedure. Infoprint Server automatically transforms the AFP data to the non-AFP data format if your administrator has specified a transform in the printer definition for the non-AFP printer in the Printer Inventory. For example, to print AFP data on a PCL printer, your administrator must specify the AFP to PCL transform in the printer definition for the PCL printer.

Example: This example shows that the **xml2afp** command transforms XML data in `myfile.xml` to AFP format in `myfile.afp`. The **lp** command prints `myfile.afp` on a PCL printer named `mypclprinter`. Infoprint Server automatically transforms the AFP data to PCL format before sending the data to the printer.

```
xml2afp -s mystyle.xml -o myfile.afp myfile.xml
lp -d mypclprinter myfile.afp
```

Tip: If your installation has installed PSF Version 3 Release 3, you can select the XML data format without specifying a filter because PSF V3R3 can process XML files using a page definition. For more information, see *PSF for OS/390 & z/OS: User's Guide*.

xml2afp

Chapter 3. Using job attributes

A job is a set of one or more documents that you submit to Infoprint Server for printing in a single printing session. A document is either a file or a group of similar files.

Infoprint Server uses *attributes* to describe jobs and the documents in jobs. For example, you can specify the number of copies of a document to print by setting a value for the **copies** attribute.

You can specify job attributes in different ways, depending on the method you use to submit a print job. Table 2 shows how to specify job attributes for different job submission methods and refers you to the section that contains more information.

Table 2. How to specify job attributes

Job submission method	How to specify job attributes	See page
z/OS UNIX lp command	-o option	52
z/OS UNIX afp2pcl , afp2pdf , and afp2ps commands	-j option	28, 35, 43 159
Print Interface subsystem	SUBSYS parameter on the DD JCL statement	139
AOPPRINT JCL procedure	OPTIONS parameter on the EXEC JCL statement	153
Infoprint Port Monitor for Windows	Infoprint Port Monitor Options dialog (select during port configuration)	172
AIX enq command	-o option	187
OS/400 LPR command	DESTOPT option	189
OS/400 remote queue defined with CRTOUTQ	Destination options field	189

Attributes are only one of the factors that determine how your job is printed. These values also affect your job:

- Print command options. For example, you can use the **-n** option of the **lp** command to specify the number of copies of a job.
- Values in the data stream. For example, the document can specify an overlay.
- Values in the page definition used to print the job. For example, the page definition can specify fonts.
- Values in the form definition used to print the job. For example, the form definition can specify duplex printing.
- Printer specifications. Infoprint Server lets the administrator specify printer characteristics for each printer.
 - The administrator can limit the jobs that a printer can accept. For example, if the administrator specifies that a certain printer can print at most 5 copies of a job and you submit a job with a value of 10 for the **copies** job attribute, your job will not be accepted.
 - The administrator can specify default values for jobs that are printed on a printer. For example, the administrator can specify the form definition that the printer uses to print jobs that are submitted without a value for the **form-definition** attribute.

- Printer setup. The way a printer is set up can affect printing. For example, if duplexing is not specified in the PCL or PostScript data stream, the printer setup determines whether documents print on one or both sides of the paper.

Abbreviations

This book shows attribute names and values in their complete form. Often, you can abbreviate attribute names and values by using the first letter of each word in the name or value. For example, you can use the abbreviation **c-c-t** for the **carriage-control-type** attribute. You can use **m** for the **machine** value, and specify the attribute and value pair as **c-c-t=m**.

Sometimes specifying only the first letter in each word is ambiguous. For example, **o-b** might stand for either **output-bin** or **overlay-back**. Here, specify enough of the name so that it is unique, as in **o-bi** and **o-ba**. If the values are ambiguous, Infoprint Server rejects the command and sends an error message.

Attributes files

You can predefine attribute and value pairs in permanent files. You can use the permanent attribute files when you need those attribute values with the **lp**, **afp2pcl**, **afp2pdf**, and **afp2ps** commands. You can also use the permanent attribute files when you need to specify those values with the AOPPRINT JCL procedure and when you use the Print Interface subsystem.

Creating an attributes file

- You can list any job attribute in an attributes file.
- You can also list the attribute attributes. Thus, an attributes file can call other attributes files.

Tip: If an attributes file calls itself, the command sends an error message.

- Attributes files must not contain any attributes without values.
- When creating an attributes file, consider spelling out the complete attribute names and attribute values rather than using abbreviations.
- You can use spaces between the attribute name and the equals sign to align the equals sign and values. This makes your files easier to read and maintain.
- You can use comment lines in attributes files. The comment starts with a number sign, **#**, and ends at the end of line.

Example: You could create an attributes file called `myatts` to request 5 copies of a job, simple duplex printing, and a specific output bin. Your file contains these lines:

```
# These are my job attributes
copies      = 5
duplex      = yes
output-bin  = collator # Collate the job
```

Tip: You can include a number sign, **#**, as part of an attribute value if you precede it immediately with a backslash, `\#`.

Using an attributes file

Use the **-o** flag to read an attributes file into the **lp** command. Use the **-j** flag to read an attributes file into the **afp2pcl**, **afp2pdf**, and **afp2ps** commands.

For example, to print a file called myfile, using the attributes in the myatts file, enter:

```
lp -o "attributes=myatts" myfile
```

This command is equivalent to this command:

```
lp -o "copies=5 duplex=yes output-bin=collator" myfile
```

For information about how to specify an attributes file with the AOPPRINT JCL procedure, see Chapter 5, “Printing using the AOPPRINT JCL procedure” on page 153.

For information about how to specify an attributes file with the Print Interface subsystem, see “JCL parameters for the Print Interface subsystem” on page 139.

Job attributes and JCL parameters

If you have previous experience with z/OS, you are accustomed to using the OUTPUT and DD statements of the Job Control Language to specify processing options for print jobs. Many job attributes correspond to parameters of the OUTPUT JCL statement. A few correspond to parameters of the DD and JOB JCL statements. For a list of JCL parameters with corresponding job attributes, see Appendix B, “JCL parameters and corresponding job attributes” on page 195.

Attribute listing

This section lists job attributes in alphabetical order.

address-text

This **multi-valued** attribute specifies one to four lines of address information that can be printed in the address field of a separator sheet.

Allowed values

You can specify one to four values. If you specify more than one value, separate the values by spaces and enclose the list of values in braces {}.

For each value, you can enter a text string of up to 60 characters. If the text string you specify contains spaces, enclose the text string in single or double quotation marks. For example:

```
-o "address-text={'Acme Novelties, Inc.' '13 Division St.'  
  'Foxboro, MA 02035' USA}"
```

If any string contains double quotation marks, enclose the string in single quotation marks.

Default value

The default text that the administrator has defined for the printer.

Usage guidelines

- Whether the text specified by this attribute is printed depends on how the administrator configures the printer's separator sheet.
- The **address-text** attribute is equivalent to the ADDRESS parameter of the OUTPUT JCL statement.

building-text

This **single-valued** attribute specifies building information that can be printed in the building field of a separator sheet.

Allowed values

You can enter a text string of up to 60 characters. If the text string you specify contains spaces, enclose the text string in single or double quotation marks. For example:

```
-o "building-text='Building 7: third floor'"
```

If the string contains double quotation marks, enclose the string in single quotation marks.

Default value

The default text that the administrator has defined for the printer.

Usage guidelines

- Whether the text specified by this attribute is printed depends on how the administrator configures the printer's separator sheet.
- This attribute is equivalent to the BUILDING parameter of the OUTPUT JCL statement.

carriage-control-type

This **single-valued** attribute identifies the type of carriage control characters that the printer device uses when interpreting and printing this document.

Allowed values

You can enter one of these fixed values:

ansi
machine
none

Default value

- For MVS data sets, such as partitioned data sets and sequential data sets, Infoprint Server determines the carriage control type from the record format in the data set control block (DCB).
- For UNIX files, such as HFS files, the default is **none**.

Usage guidelines

- This attribute is most useful for line data documents.
- Use this attribute when you print UNIX files (files in a hierarchical file system) that contain carriage controls.
- For MVS data sets, Infoprint Server determines the carriage control type from the data set. When processing MO:DCA-P (including mixed mode) UNIX files, Infoprint Server usually determines the correct carriage control type. Infoprint Server might be able to properly detect UNIX files that contain line data with machine carriage controls, but for other types of line data in UNIX files, you probably need to specify **document-format = line**, and if the carriage control type is ansi, **carriage-control-type = ansi**. For other formats printed from a UNIX file, the default is correct.

chars

This **multi-valued** attribute identifies from one to four coded fonts that are used to print a line data document or a MO:DCA document in which no fonts are specified.

A coded font is a pair of a character set and a code page. Coded font names begin with a 2-character prefix (X0 or XZ), followed by up to 4 alphanumeric characters. X042B2 is an example of a coded font name. For more information about coded fonts, see *IBM AFP Fonts: Font Summary for AFP Font Collection*.

Allowed values

You can enter a text string that contains the names of the coded fonts. The name of each font can be 1 to 4 characters.

Tip: Some coded fonts have 6-character names, not counting the prefix. For these coded fonts, see *IBM AFP Fonts: Font Summary for AFP Font Collection* for the 4-character alternate coded font name.

Omit the 2-character prefix from the coded font name or the alternate coded font name.

If you specify more than one coded font, separate the font names by spaces and surround the string of font names with braces. For example:

```
-o "chars={GT10 GT12}"
```

Default values

1. The default coded fonts that the administrator has defined for the printer.
2. The coded fonts that the page definition used to print the job specifies.

Usage guidelines

- This attribute is most useful for line data documents.
- This attribute applies to line data documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- PSF for OS/390 uses this attribute only if the page definition used to print the job does not specify fonts, or if the default page definition is used.
- The AFP to PCL, AFP to PDF, and AFP to PostScript transforms use this attribute only if the page definition used to print the job does not specify fonts.
- If you specify more than one coded font with the **chars** attribute, the job must contain either shift-out-shift-in (SOSI) codes or table reference characters (TRCs) to use coded fonts other than the first one. IBM recommends that you do not mix SOSI codes and TRCs.
 - If the job contains TRCs, you must specify the **table-reference-characters** attribute value as **true**. PSF and the AFP to PCL, AFP to PDF, and AFP to PostScript transforms use the TRC characters to select the corresponding coded font specified with the **chars** attribute.
 - If the job contains SOSI codes, PSF and the AFP to PCL, AFP to PDF, and AFP to PostScript transforms use the first coded font specified with the **chars** attribute as the single-byte font and the second coded font as the double-byte font.

For more information about using multiple coded fonts, see *AFP: Programming Guide and Line Data Reference* and *PSF for OS/390 & z/OS: User's Guide*.

- Raster fonts are used unless the administrator has requested font mapping to outline fonts and your font name is in the font mapping table.
- This attribute is equivalent to the CHARS parameter of the OUTPUT and DD JCL statements.

copies

This **single-valued** attribute specifies the number of copies of each document in the job to print.

Allowed values

You can enter an integer from 1 to 32640.

Default value

1. The default value that the administrator has defined for the printer.
2. 1

Usage guidelines

- Only one copy prints when you print on VTAM-controlled printers or on Internet Printing Protocol (IPP) printers that do not support the **copies** IPP job attribute.
- Only one copy of the file is sent to an e-mail destination.
- The administrator can limit the number of copies that you can specify. Before accepting a job, Infoprint Server verifies that the printer can support the value of this attribute.
- The value you specify for this attribute overrides any value in the form definition that is used to print the job.
- This attribute is similar to the COPIES parameter of the OUTPUT and DD JCL statements.

department-text

This **single-valued** attribute specifies department information that can be printed in the department field of a separator sheet.

Allowed values

You can enter a text string of up to 60 characters. If the text string you specify contains spaces, enclose the text string in single or double quotation marks. For example:

```
-o "department-text='Customer Relations'"
```

If the string contains double quotation marks, enclose the string in single quotation marks.

Default value

The default text that the administrator has defined for the printer.

Usage guidelines

- Whether the text specified by this attribute is printed depends on how the administrator configures the printer's separator sheet.
- This attribute is equivalent to the DEPT parameter of the OUTPUT JCL statement.

document-codepage

This **single-valued** attribute is the name of the code page used to create the document. Infoprint Server uses this name as the source when it uses the z/OS UNIX iconv utility to convert data from one code page to another.

Allowed values

You can enter the name of a code page. For the names of code pages that the iconv utility supports, see *z/OS C/C++ Programming Guide*.

Default value

1. The default code page that the administrator has defined for the printer.
2. The code page for the current locale of z/OS UNIX System Services. This is usually an EBCDIC code page.

Usage guidelines

- To print an ASCII job, you must use an ASCII code page. If the printer is not defined to use an ASCII code page, you must specify one as the value of this attribute. ISO8859-1 is an example of an ASCII code page.
- Infoprint Server uses this attribute to translate documents before placing them on the Job Entry Subsystem (JES) spool. Because Infoprint Server does not translate data streams such as MO:DCA-P, PCL, or PostScript, it ignores this attribute when printing these data streams.

document-format

This **single-valued** attribute identifies the format (data type) of this document.

Allowed values

You can enter one of these fixed values:

line-data

A data format whose bytes map to characters. Line data is stored as records, for example, in sequential data sets. The records can contain carriage-control characters and table-reference characters. Line data is typically found in mainframe data sets.

text A data format whose bytes map to characters. Text data contains no control characters other than line feed (LF), carriage return (CR), horizontal tab (HT), vertical tab (VT), and form feed (FF). Text data is typically found in workstation files.

modca-p

Mixed Object Document Content Architecture Presentation (MO:DCA-P) data format, defined by IBM.

pcl Printer Control Language (PCL) data format, defined by Hewlett-Packard.

pdf Portable Document Format (PDF) data format, defined by Adobe.

postscript

PostScript data format, defined by Adobe.

sap SAP Output Text Format (OTF) or SAP Advanced Business Application Programming (ABAP) Version 1 or Version 2 data format, defined by SAP AG.

xml Extensible Markup Language, which includes Extensible Stylesheet Language formatting objects (XSL-FO).

other Any other data format.

Default value

The value that Infoprint Server determines from the contents of the data stream.

Usage guidelines

Before accepting a job, Infoprint Server verifies that the printer can support the value of this attribute.

document-type

This **single-valued** attribute indicates that the document is either a printable document or a list of printable documents.

Allowed values

You can enter one of these fixed values:

- **file-reference**
- **printable**

Default value printable

Usage guidelines

- A printable document contains data that you want to print.
- A file-reference document is a list of similar printable documents. Separate the document names with spaces, tabs, or new lines. For example:

```
file1.txt  
file2.txt  
file3.txt
```

All these documents must have the same format, because Infoprint Server processes them all the same way.

- Do not combine file-reference documents and printable documents in the same job.
- Do not specify this job attribute in the SUBSYS JCL parameter.

duplex

This **single-valued** attribute indicates whether to print on one or both sides of the paper and the relative orientation of consecutive pages.

Allowed values

You can enter one of these fixed values:

- no** The job is printed on one side of the paper.
- yes** The job is printed on both sides of the paper so that the top of side 1 is the top of side 2 (for side binding).
- tumble** The job is printed on both sides of the paper so that the top of side 1 is the bottom of side 2 (for top binding).

Default value

1. The default value that the administrator has defined for the printer.
2. The value in the form definition used to print the job.

Usage guidelines

- This attribute applies only to documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- The value you specify for this attribute overrides any value in the form definition used to print the job.
- Before accepting a job, Infoprint Server verifies that the printer can support the value of this attribute.

- This attribute is equivalent to the DUPLEX parameter of the OUTPUT JCL statement.

filter-options

This **single-valued** attribute lets you pass options to a filter that converts this document from one data format to another. For example, you can pass options to these filters:

- A transform filter that Infoprint Server Transforms or another optional transform product provides
- The Infoprint Server LPD compatibility filter (**lpd_compat.so**)
- The Infoprint Server remote transform filter (**aoprform.dll**)
- A filter written by your installation

Allowed values

You can enter a text string that contains the options. If the string contains blanks, enclose the string in single or double quotation marks. For example:

```
-o "filter-options='-p 5-12 -p 21-30'"
```

For information about which options the transform filters accept, see the description of the **pcl2afp**, **pdf2afp**, **ps2afp**, **sap2afp**, **afp2pcl**, **afp2ps**, and **afp2pdf** commands in Chapter 2, “Printing from z/OS UNIX System Services using Infoprint Server commands” on page 23.

For information about which options the remote transform filter (**aoprform.dll**) accepts, see *z/OS Infoprint Server Operation and Administration*.

For information about filter options for the **xml2afp** command, see *Infoprint XML Extender for z/OS*.

The LPD compatibility filter (**lpd_compat.so**) lets you specify options that correspond to parameters you can specify on the z/OS Communications Server (TCP/IP) LPR command. It accepts these options:

-f filter Specifies the type of filter processing. This option corresponds to the FILTER parameter of the TCP/IP LPR command. The default value is **f**. Valid values are:

Filter	Meaning
f	Paginate the data, but do not add a heading. Truncate lines that exceed the maximum width. Discard any ASCII control characters except CR, FF, LF, BS, NL, VT, and HT.
l	Do not paginate the data or add a heading. Pass through all control characters.
p	Paginate the data, adding a heading to each page. The heading includes the date and time that Infoprint Server received the data, the title, and the page number. After a page of text, a new page is started with a new page number. Truncate lines that exceed the maximum width.
r	Interpret the first column of each input line as an ANSI (FORTRAN) carriage control. The ANSI standard limits this to blank, “1”, “0”, “+”, and “-” carriage controls. Truncate lines that exceed the maximum width.

-l length

Specifies the maximum number of lines to include on a page. This value applies only to filters **f** and **p**. This option corresponds to the LINECOUNT parameter of the TCP/IP LPR command. The default value is 60 lines. To prevent Infoprint Server from inserting page breaks, specify 0.

-w width

Specifies the maximum number of columns to allow on a line. Lines longer than the number specified (except for the title line) are truncated. The number specified does not include the carriage control character at the beginning of each line. This value applies only to filters **f**, **p**, and **r**. This option corresponds to the WIDTH parameter of the TCP/IP LPR command. The default action is that lines are not truncated.

For examples that show how to specify this attribute on the **lp** command, see “Transform and print a job” on page 56 and “Paginate line data and print with a header on each page” on page 58.

Default value

The default filter options that the administrator has defined for the printer. If the administrator has not defined a filter option, the default value for the option is used.

Usage guidelines

- The filter options you specify in this attribute take effect only if the administrator specifies the filter for the printer in the Printer Inventory. The administrator can also specify filter options in the Printer Inventory.
- The administrator can control whether the filter options that you specify with this attribute are used. For information about how the administrator can control whether your filter options take effect, see the description of the **%filter-options** option in *z/OS Infoprint Server Operation and Administration*.
- The LPD compatibility filter can be used for text and line data when printing to an AFP printer or a JES line printer. For more information about this filter, see *z/OS Infoprint Server Operation and Administration*.

form-definition

This **single-valued** attribute identifies the form definition used when printing this document.

Allowed values

You can enter a text string of up to 8 characters that contains the identification for this resource. You can specify the form definition name either with or without the **F1** prefix.

Default value

The default form definition that the administrator has defined for the printer.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- If the document has an inline form definition, specify either the name of that form definition or **dummy**.
- You can instruct the AFP to PCL, AFP to PDF, and AFP to PostScript transforms to select a form definition from your user library rather than from a system library assigned to the transforms. To use a form definition from a user library:

1. Refer to the user library containing the form definition in the **resource-library** attribute.
 2. Specify the name of the form definition in the **form-definition** attribute.
- This attribute is equivalent to the FORMDEF parameter of the OUTPUT JCL statement.

forms

This **single-valued** attribute identifies the form (medium) on which this job is printed.

Allowed values

You can enter a text string of up to 8 characters.

Default value

1. The default form that the administrator has defined for the printer.
2. The default form that the administrator has defined for the installation.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- Before accepting a job, Infoprint Server verifies that the printer can support the value of this attribute.
- This attribute is equivalent to the FORMS parameter of the OUTPUT JCL statement.

hold

This **single-valued** attribute indicates whether Infoprint Server holds all data sets in the job on the JES spool.

Allowed values

You can enter one of these fixed values or synonyms:

Fixed Value	Input Synonym
true	yes
false	no

Default value

1. The default value that the administrator has defined for the printer.
2. **false**

Usage guidelines

- A held job remains in the queue until the z/OS operator releases it.

input-tray

This **single-valued** attribute identifies an input tray on the printer device that contains the medium used for normal document pages.

Allowed values

You can enter any value that the administrator has defined. Some typical values are:

alternate
bottom
envelope

large-capacity
main
manual
middle
side
top

Default value

1. The default input tray that the administrator has defined for the printer.
2. The input tray that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or automatically transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This attribute does not apply to data transformed to another format using the **afp2pcl**, **afp2pdf**, or **afp2ps** command.
- When you use this attribute with the **lp** command and data is being transformed from AFP format, the value on this attribute is mapped to an input-tray-number value. For example, **letter** might be mapped to **input-tray-number=2**.

The input-tray-number is then mapped to the appropriate printer tray. For example, **2** might be mapped to **PCL input tray 4**. In this example, if you specify **letter** on this attribute and the AFP file is being transformed automatically to PCL, the PCL printer will use input tray 4.

For the default input-tray-number mapping, see “Usage guidelines”. Your system programmer defines the mapping from input-tray to input-tray-number in the printer definition.

- Before accepting a job, Infoprint Server verifies that the printer can support the value of this attribute.
- The value you specify for this attribute overrides any input tray selection in the data stream or form definition.
- If the tray name contains blanks or special characters, enclose the name in single or double quotation marks.
- This attribute is similar to the INTRAY parameter of the OUTPUT JCL statement.

input-tray-number

This **single-valued** attribute identifies an input tray number on the printer device that contains the medium used for normal document pages.

Allowed values

You can enter any number that the AFP printer supports. Some typical values are:
1–255

Default value

1. The default input tray that the administrator has defined for the printer.
2. The input tray that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- The value you specify for this attribute overrides any input tray selection in the data stream or form definition.

- This attribute is equivalent to the INTRAY parameter of the OUTPUT JCL statement.
- These guidelines only apply to the AFP to PCL, AFP to PDF, and AFP to PostScript transforms:
 - Your administrator sets up the mapping of AFP printer tray numbers to PCL, PDF, or PostScript printer tray numbers. All values greater than 9 map to the same PCL, PDF, or PostScript printer tray number. The defaults are tray 2 for PCL and PostScript output, tray 1 for PDF output.
 - For PDF output, the page size for the entire document is the size of paper the administrator specifies for the selected printer tray.
 - Always specify the AFP printer input bin number, not the PCL, PDF, or PostScript bin number, on this attribute. When you print on a PCL, PDF, or PostScript printer, the transforms use the tray number of the AFP printer to select a corresponding input tray number for the PCL or PostScript printer. The default mapping is shown in Table 3. For example, if you want to print from input tray 4 on a PCL printer, specify `input-tray-number=2`. Contact your administrator to confirm this mapping is valid for the transform you are using.

Table 3. *input-bin-number default mapping*

Data stream	Mapping
PCL	1,4,0,0,0,0,0,0,2
PostScript	1,2,0,0,0,0,0,0,2
PDF	1,1,1,1,1,1,1,1,1
Tip: “0” indicates that the paper tray is not installed.	

jes-priority

This **single-valued** attribute indicates the scheduling priority for the job.

Allowed values

You can enter an integer from 0 to 255.

Default value

The default value that the administrator has defined for the printer.

Usage guidelines

- 255 is the highest priority. 0 is the lowest.
- If the z/OS system is not configured to honor priority values, it ignores this attribute.
- This attribute is equivalent to the PRTY parameter of the OUTPUT JCL statement.

name-text

This **single-valued** attribute specifies name information that can be printed in the name field of a separator sheet.

Allowed values

You can enter a text string of up to 60 characters. If the text string you specify contains spaces, enclose the text string in single or double quotation marks. For example:

```
-o "name-text='C. J. Brown'"
```

If the string contains double quotation marks, enclose the string in single quotation marks.

Default value

The default text that the administrator has defined for the printer.

Usage guidelines

- Whether the text specified by this attribute is printed depends on how the administrator configures the printer's separator sheet.
- This attribute is equivalent to the NAME parameter of the OUTPUT JCL statement.

output-bin

This **single-valued** attribute specifies the name of the output bin to which you want Infoprint Server to direct the output from your job.

Allowed values

You can enter any value that the administrator has defined. Some typical values are:

bottom
collator
face-down
face-up
large
left
middle
private
right
side
top

Default value

1. The default output bin that the administrator has defined for the printer.
2. The output bin that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or automatically transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This attribute does not apply to data transformed to another format using the command **afp2pcl**, **afp2pdf**, or **afp2ps**.
- Before accepting a job, Infoprint Server verifies that the printer can support the value of this attribute.
- The value you specify for the **output-bin** attribute overrides any output bin that the form definition used to print the job specifies.
- If the bin name contains blanks or special characters, enclose the name in single or double quotation marks.
- This attribute is similar to the OUTBIN parameter of the OUTPUT JCL statement.

output-bin-number

This **single-valued** attribute specifies the number of the output bin to which you want Infoprint Server to direct the output from your job.

Allowed values

You can enter any number that the AFP printer supports. Some typical values are:
1–16

Default value

1. The default output bin that the administrator has defined for the printer.
2. The output bin that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- When you print on a PCL or PostScript printer, instead of on an AFP printer, specify the output bin number of the PCL or PostScript printer.
- The value you specify for the **output-bin-number** attribute overrides any output bin that the form definition used to print the job specifies.
- This attribute is equivalent to the OUTBIN parameter of the OUTPUT JCL statement.

overlay-back

This **single-valued** attribute specifies the name of an overlay that PSF and the AFP to PCL, AFP to PDF, and AFP to PostScript transforms place on the back of each page in a two-sided job. An overlay contains predefined data, such as lines, shading, text, boxes, or logos that can merge with variable data on a page.

Allowed values

You can enter an overlay name of up to 8 characters. The first character must be alphabetic. Note that for overlays, unlike form definitions and page definitions, you must specify the complete name, including the **O1** prefix.

Default value

The default overlay that the administrator has defined for the printer.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This overlay prints in addition to any overlay specified by the form definition for the job.
- This attribute is equivalent to the OVERLAYB parameter of the OUTPUT JCL statement.

overlay-front

This **single-valued** attribute specifies the name of an overlay that PSF and the AFP to PCL, AFP to PDF, and AFP to PostScript transforms place on the front of each page in the job. An overlay contains predefined data, such as lines, shading, text, boxes, or logos that can merge with variable data on a page.

Allowed values

You can enter an overlay name of up to 8 characters. The first character must be alphabetic. Note that for overlays, unlike form definitions and page definitions, you must specify the complete name, including the **O1** prefix.

Default value

The default overlay that the administrator has defined for the printer.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This overlay prints in addition to any overlay specified by the form definition for the job.
- This attribute is equivalent to the OVERLAYF parameter of the OUTPUT JCL statement.

page-definition

This **single-valued** attribute identifies the page definition used to print a line data document.

Allowed values

You can enter a text string of up to 8 characters. You can specify the page definition name either with or without the **P1** prefix.

Default value

The default page definition that the administrator has defined for the printer.

Usage guidelines

- This attribute applies to line data documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- If the document has an inline page definition, specify either the name of that page definition or **dummy**.
- This attribute is equivalent to the PAGEDEF parameter of the OUTPUT JCL statement.

print-error-reporting

This **single-valued** attribute indicates the type of data fidelity problems (print-positioning errors or invalid-character errors) that the printer reports while printing this document.

Allowed values

You can enter one of these fixed values:

all	Report both print-positioning and invalid-character errors.
character	Report only invalid-character errors.
none	Report no errors.
position	Report only print-positioning errors.

Default value

The default value that the administrator has defined for the printer.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer.
- Before accepting a job, Infoprint Server verifies that the printer can support the value of this attribute.
- This attribute is similar to the DATAACK parameter of the OUTPUT JCL statement.

print-queue-name

This **single-valued** attribute specifies the name of the print queue on the target printer.

Allowed values

You can enter a text string up to 127 characters.

Default value

The default print queue that the administrator has defined for the printer.

Usage guidelines

- The value in this attribute overrides the print queue name specified in the printer definition. You must use this attribute for local area network (LAN) printers not defined by your administrator.
- If the printer definition does not specify the LPR protocol, IP PrintWay ignores this parameter.
- This attribute is equivalent to the PRTQUEUE parameter of the OUTPUT JCL statement.

printer-ip-address

This **single-valued** attribute identifies the Internet Protocol (IP) address of the target printer.

Allowed values

You can enter a text string of up to 115 characters. The string must be one of these types of address:

Dotted decimal address

A series of integers in the range of 0 to 255, separated by periods (decimal address). For example:

9.99.12.85

Host name

A series of domain names that can contain alphanumeric characters and dashes (–), separated by periods (.). The first character must be alphabetic or numeric. For example:

printer1.boulder.IBM.com

Note: Do not enter an IP address in the colon-hexadecimal format because Infoprint Server does not currently support this format.

Default value

The IP address that the administrator has defined for the printer.

Usage guidelines

- The value in this attribute overrides the IP address specified in the printer definition. Use this attribute when you submit jobs to LAN printers not defined by your administrator.
- If the printer definition does not specify the LPR or direct sockets printing protocol, IP PrintWay ignores this parameter.
- When you specify this attribute, you must also specify the **print-queue-name** attribute.
- For printers attached using the i-data 7913 Intelligent Printer Data Stream™ (IPDS™) Printer LAN Attachment, use the IP address of the 7913.

- This attribute is equivalent to the DEST=IP parameter of the OUTPUT JCL statement.

resource-library

This **multi-valued** attribute defines the location for document-specific resources: fonts, form definitions, overlays, and page definitions.

Allowed values

You can enter up to 8 names of cataloged MVS data sets. Each name can be up to 44 characters. Separate multiple library names with spaces and surround the string of library names with braces. For example:

```
-o 'resource-library={FONT.LIBRARY OVERLAY.LIBRARY}'
```

Default values

1. The default resource libraries that the administrator has defined for the printer.
2. PSF or the AFP to PCL, AFP to PDF, or AFP to PostScript transform determine the resource libraries.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- If PSF or the AFP to PCL, AFP to PDF, or AFP to PostScript transform cannot find a resource, it processes the job and prints error messages at the end of the job. Infoprint Server reports the job as completed.
- All libraries used with the AFP to PCL, AFP to PDF, or AFP to PostScript transform must be defined to RACF with universal read access.
- This attribute is equivalent to the USERLIB parameter of the OUTPUT JCL statement.

room-text

This **single-valued** attribute specifies room information that can be printed in the room field of a separator sheet.

Allowed values

You can enter a text string of up to 60 characters. If the text string you specify contains spaces, enclose the text string in single or double quotation marks. For example:

```
-o "room-text='Room 306-B'"
```

If the string contains double quotation marks, enclose the string in single quotation marks.

Default value

The default text that the administrator has defined for the printer.

Usage guidelines

- Whether the text specified by this attribute is printed depends on how the administrator configures the printer's separator sheet.
- This attribute is equivalent to the ROOM parameter of the OUTPUT JCL statement.

shift-out-shift-in

This **single-valued** attribute specifies the printer scanning modes used when processing EBCDIC line data that prints with either a single-byte or a double-byte font.

Allowed values

You can enter one of these fixed values:

- one** PSF or the AFP to PCL, AFP to PDF, or AFP to PostScript transform converts each shift-out, shift-in code to a blank and a Set Coded Font Local text control.
- two** PSF or the AFP to PCL, AFP to PDF, or AFP to PostScript transform converts each shift-out, shift-in code to a Set Coded Font Local text control.
- three** PSF or the AFP to PCL, AFP to PDF, or AFP to PostScript transform converts each shift-in code to a Set Coded Font Local text control and two blanks. It converts each shift-out code to a Set Coded Font Local text control.

Default value

The default value that the administrator has defined for the printer.

Usage guidelines

- This attribute applies only to line data documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- For the shift-in, shift-out process to work correctly, either the **chars** attribute or the page definition used to print the job must specify two coded fonts. The first must be a single-byte font, and the second must be a double-byte font.
- IBM recommends that you do not mix SOSI codes and TRCs in the same job.
- This attribute is similar to the PRMODE parameter of the OUTPUT JCL statement.

sysout-dataset-name

This **single-valued** attribute specifies the name to assign to the system output data sets (sysout data sets) that Infoprint Server creates on the JES spool. It becomes the last qualifier of the fully qualified data set name on the JES spool. The fully qualified data set name can be printed on a separator page created by your installation. It can also be printed on a separator page (banner page) printed by the printer's LPD. If the file is sent to an e-mail destination instead of to a printer, the name you specify in this parameter is used as the name of the e-mail attachment.

Allowed values

You can enter a text string of up to 8 characters. The first character must be a letter or a national (#, \$, @) character. Other characters can be letters, numbers, or national (#, \$, @) characters. If the text string contains #, \$, or @, enclose the text string in single or double quotation marks. For example:

```
-o "sysout-dataset-name='$MYFILE'"
```

Lowercase letters are converted to uppercase letters.

Default value

The last 8 characters of the name of the file. If the first character is not a letter, #, \$, or @, it is converted to a #. If one of the remaining characters is not a letter, number, #, \$, or @, it is converted to a #.

Usage guidelines

- If you use the Print Interface subsystem, the **lpstat** command displays this name.
- If you do not use the Print Interface subsystem, the **lpstat** command displays the original file name instead of this name to provide more information about the file.
- This attribute is similar to the DSNAMES parameter of the DD JCL statement.

sysout-job-id

This **single-valued** attribute specifies the job ID to assign to the system output data sets (sysout data sets) that Infoprint Server creates on the JES spool. The system operator can use this job ID to locate the sysout data sets on the JES spool.

Allowed values

You can enter a text string of up to 8 characters. The first character must be a letter or a national (#, \$, @) character. Other characters can be letters, numbers, or national (#, \$, @) characters. If the text string contains #, \$, or @, enclose the text string in single or double quotation marks. For example:

```
-o "sysout-job-id='#123'"
```

Lowercase letters are converted to uppercase letters.

Default value

- If you use the Print Interface subsystem, the job ID that z/OS assigns to your job is used.
- If you do not use the Print Interface subsystem, the Infoprint Server job ID is used. The Infoprint Server job ID is a unique identifier composed of the 2-character prefix specified in the Infoprint Server configuration file, **aopd.conf**, followed by a unique number. You can use this number to query or cancel your job with the **lpstat** or **cancel** commands.

Usage guidelines

- You cannot use the value you specify to query or cancel your job with the **lp** or **lpstat** command.
- The job ID you specify is not written in the SMF type 6 accounting record that either IP PrintWay or PSF writes.
- JES commands do not display this job ID. JES commands display the job ID that z/OS assigns to the job.

sysout-job-name

This **single-valued** attribute specifies the job name to assign to the system output data sets (sysout data sets) that Infoprint Server creates on the JES spool. The system operator can use this job name to locate the sysout data sets on the JES spool. This name can be printed on a separator page created by your installation. It can also be printed on a separator page (banner page) printed by the printer's LPD.

Allowed values

You can enter a text string of up to 8 characters. The first character must be a letter or a national (#, \$, @) character. Other characters can be letters, numbers, or national (#, \$, @) characters. If the text string contains #, \$, or @, enclose the text string in single or double quotation marks. For example:

```
-o "sysout-job-name='$MYJOB'"
```

Lowercase letters are converted to uppercase letters.

Default value

- If you use the Print Interface subsystem, the job name specified on the JOB JCL statement, or the name assigned by the z/OS system, is used.
- If you do not use the Print Interface subsystem, the first 8 characters of your user ID are used.

Usage guidelines

- Whether the job name specified by this attribute is printed depends on how your administrator configures the printer's separator sheet or how the printer's LPD is implemented.
- The job name you specify is written in the SMF type 6 accounting record that either IP PrintWay or PSF writes.
- This attribute is equivalent to the job name you can specify on a JOB JCL statement.

table-reference-characters

This **single-valued** attribute specifies whether the document contains table-reference characters (TRCs). A TRC selects a font character set named by the **chars** attribute or in the page definition used to print the job. A TRC is the first character of each line in the document unless the first character is a carriage control character. In that case, the TRC is the second character.

Allowed values

You can enter one of these fixed values or synonyms:

Fixed Value:	Input Synonym:
true	yes
false	no

Default value

The default value that the administrator has defined for the printer.

Usage guidelines

- This attribute applies only to line data documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- If the value of this attribute is **true** and the page definition does not identify fonts, you must specify fonts with the **chars** attribute.
- If the line data contains TRCs and you do not specify this attribute, your printed output will not be correct. PSF or the AFP to PCL, AFP to PDF, or AFP to PostScript transform interprets the TRCs as text characters instead of font identifiers.
- IBM recommends that you do not mix SOSI codes and TRCs in the same job.
- This attribute is equivalent to the TRC parameter of the OUTPUT JCL statement.
- For more information about using table-reference characters, see *AFP: Programming Guide and Line Data Reference*.

title-text

This **single-valued** attribute describes the contents of the file. This value can be printed on a separator page created by your installation. It can also be printed on a separator page (banner page) printed by the printer's LPD. If the file is sent to an e-mail destination, this value is the subject of the e-mail.

Allowed values

You can enter a text string of up to 60 characters. If the text string you specify contains spaces, enclose the text string in single or double quotation marks. For example:

```
-o "title-text='Meeting Agenda'"
```

If the string contains double quotation marks, enclose the string in single quotation marks. For example:

```
-o "title-text='A New Interpretation of "Finnegans Wake"'"
```

Default value

- For a separator page created by an IP PrintWay or PSF exit: The default value is the title your administrator specified in the Allocation section of the printer definition. If none is specified, there is no default value.
- For the LPD's separator page: The default value is the title your administrator specified in the Allocation section of the printer definition. If none is specified, the default value is the title or filename your administrator specified in the Protocol section of the printer definition. If none is specified, the default value is the data set name.
- For the subject of an e-mail: The default value is the title specified in the Allocation section of the printer definition. If none is specified, the default value is the job name. Depending on how the print request was submitted, the job name might be the ID of the user who submitted the print request.

Usage guidelines

- Whether the text specified by this attribute is printed depends on how your administrator configures the printer's separator sheet or how the LPD is implemented.
- This attribute is equivalent to the TITLE parameter of the OUTPUT JCL statement.

x-image-shift-back

This **single-valued** attribute specifies the X offset of the logical page origin to the right of the physical page origin on the back side of a double-sided sheet.

Allowed values

You can enter a number from 000.000 to 999.999, followed by the unit of measure (optional). The default unit of measure is millimeters. No blank spaces are allowed. These units are valid:

Unit	Meaning
IN	Inches
CM	Centimeters
MM	Millimeters (default unit)
PELS	Picture elements (1/240 inch)
POINTS	Points (1/72 inch)

For example, you can enter these values:

x-image-shift-back=25.4
x-image-shift-back=25.4MM
x-image-shift-back=2.54CM
x-image-shift-back=1IN
x-image-shift-back=240PELS
x-image-shift-back=72POINTS

Default value

1. The default X offset that the administrator has defined for the printer.
2. The X offset that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This attribute overrides the X-offset value in the form definition used to print the job.
- This attribute is similar to the OFFSETXB parameter of the OUTPUT JCL statement.

x-image-shift-front

This **single-valued** attribute specifies the X offset of the logical page origin to the right of the physical page origin on the front of the sheet.

Allowed values

You can enter a value from 0 through 999.999, followed by the unit of measure (optional). The default unit of measure is millimeters. No blanks are allowed. For information about the allowed values, see “x-image-shift-back” on page 106.

Default value

1. The default X offset that the administrator has defined for the printer.
2. The X offset that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This attribute overrides the X-offset value in the form definition used to print the job.
- This attribute is similar to the OFFSETXF parameter of the OUTPUT JCL statement.

y-image-shift-back

This **single-valued** attribute specifies the Y offset of the logical page origin below the physical page origin on the back side of a double-sided sheet.

Allowed values

You can enter a value from 0 through 999.999, followed by the unit of measure (optional). The default unit of measure is millimeters. No blanks are allowed. For information about the allowed values, see “x-image-shift-back” on page 106.

Default value

1. The default Y offset that the administrator has defined for the printer.
2. The Y offset that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This attribute overrides the Y-offset value in the form definition used to print the job.
- This attribute is similar to the OFFSETYB parameter of the OUTPUT JCL statement.

y-image-shift-front

This **single-valued** attribute specifies the Y offset of the logical page origin below the physical page origin on the front of the sheet.

Allowed values

You can enter a value from 0 through 999.999, followed by the unit of measure (optional). The default unit of measure is millimeters. No blanks are allowed. For information about the allowed values, see “x-image-shift-back” on page 106.

Default value

1. The default Y offset that the administrator has defined for the printer.
2. The Y offset that the form definition used to print the job specifies.

Usage guidelines

- This attribute applies to line data and AFP documents printed on an IBM AFP printer or transformed to another format using the AFP to PCL, AFP to PDF, or AFP to PostScript transform.
- This attribute overrides the Y-offset value in the form definition used to print the job.
- This attribute is similar to the OFFSETYF parameter of the OUTPUT JCL statement.

Chapter 4. Printing from batch applications using DD and OUTPUT JCL statements

This chapter describes how to code the OUTPUT and DD statements of the Job Control Language to use Infoprint Server to process an output data set. It describes how to:

- Print output data sets using the IP PrintWay component of Infoprint Server. IP PrintWay can transmit an output data set to a printer or print server in your TCP/IP network or to a VTAM-controlled printer. IP PrintWay can also send an output data set to an e-mail destination.
- Transform data from one data format to another format and print it on any printer.

Printing output using IP PrintWay

To use IP PrintWay to print an output data set, you must specify the Job Entry Subsystem work-selection criteria that your administrator has defined for the IP PrintWay output writer (also known as the IP PrintWay FSA). Examples of JES work-selection criteria are a JES output class or a writer name. For example, if your administrator has defined the IP PrintWay FSA to select output data sets from the JES spool in JES output class P, you would specify class P on your OUTPUT or DD statement. Ask your administrator for the appropriate work-selection values to specify.

If you use the Print Interface subsystem, and your administrator has specified the JES work-selection criteria in the printer definition in the Printer Inventory, you do *not* need to specify the JES work-selection criteria in the JCL. For example, if your administrator has specified class P as the JES output class in the printer definition, you do not need to specify class P on your OUTPUT statement.

To direct your output to a particular printer or e-mail destination, you can use one of these methods, which are described in more detail in the next sections:

- Specify the name of the printer definition your administrator defined in the Printer Inventory.
- Specify the output class, destination name, or form name that your administrator assigned to the printer definition in the Printer Inventory.
- Specify the printer's IP address and either print queue name or port number.

Specifying the printer definition name

You can specify the printer definition name in the FSSDATA='printer' parameter on the OUTPUT JCL statement. If you use the Print Interface subsystem, you can instead specify the printer definition name in the SUBSYS parameter on the DD JCL statement. The printer definition name is case-sensitive and must exactly match the name of the printer definition created by your administrator in the Infoprint Server Printer Inventory.

Typically, IP PrintWay uses the IP address in the named printer definition to locate the printer. However, if you also specify an IP address in the DEST=IP parameter of the OUTPUT JCL statement, IP PrintWay uses that address to locate the printer instead of the address in the printer definition. You might want to specify the printer's IP address in the DEST=IP parameter when your administrator has not created a printer definition for your printer.

Related information: For an example, see “Direct output to IP PrintWay and to a printer by specifying the printer definition name” on page 144.

Specifying class, destination, or form

If you do not know the printer definition name, you can specify a value for at least one of the CLASS, DEST, and FORMS parameters on the OUTPUT JCL statement. You can specify any or all of these values. IP PrintWay sends the print data set to a printer or e-mail destination whose printer definition matches the values that you specify. Ask your administrator to determine the values that you can specify.

Related administrative task: The administrator must specify the CLASS, DEST, and FORMS values in the printer definition and select the **Use DEST, CLASS, and FORMS for IP PrintWay printer selection** option in the printer definition.

Limitation: If you use the Print Interface subsystem, you *cannot* use the CLASS, DEST, and FORMS JCL parameters to select the printer definition. Instead, you must specify the name of the printer definition.

Related information: For an example, see “Direct output to IP PrintWay and to a printer by specifying DEST, CLASS, or FORMS” on page 145.

Specifying the printer’s IP address

To print a data set on a printer for which your administrator has not created a printer definition, specify the DEST=IP parameter on the OUTPUT JCL statement. Specify the IP address or host name of the printer or the system to which the printer is attached. When you specify DEST=IP, you must also specify either the PRTQUEUE parameter or the PORTNO parameter on the OUTPUT JCL statement.

If you also specify the name of a printer definition in either the FSSDATA or SUBSYS parameter, IP PrintWay uses printing options specified in that printer definition, but uses the printer’s IP address specified in the DEST=IP parameter. If you do not specify the name of a printer definition, IP PrintWay uses printing options specified in the IP PrintWay default printer definition.

Limitation: If the resubmit for filtering function is used, do *not* code the DEST=IP, PRTQUEUE, and PORTNO parameters on the OUTPUT JCL statement because IP PrintWay ignores these parameters and instead uses the IP address, print queue name, and port number in the printer definition.

Related information: For an example, see “Direct output to IP PrintWay and to a printer by specifying a host name or an IP address” on page 145.

Sending output to an e-mail destination

When you submit a print request, you can send the file to an e-mail destination instead of to a printer. When you send a file to an e-mail destination, your administrator can specify the e-mail address list of the recipients in the printer definition in the Printer Inventory, or you can specify the address list in an alias file that your administrator defines to z/OS UNIX sendmail.

The e-mail has these characteristics:

- Each output data set is a separate e-mail attachment. The name of the attachment is the value specified in the DSNAME parameter on the DD statement for the output data set. If none is specified, the job name is used.

In a JES2 environment, if your job creates multiple output data sets that JES2 places in the same output subgroup, IP PrintWay can send the output data sets as attachments in the *same* e-mail. To obtain this function, your administrator must select the **Concatenate job** option in the **Dataset grouping** field in the printer definition.

For more information about when JES groups data sets in the same output subgroup, see *z/OS JES2 Initialization and Tuning Guide*.

Limitation: JES2 output grouping is *not* supported when either the resubmit for filtering function or the Print Interface subsystem is used. In these situations, each output data set is sent in a separate e-mail attachment.

- The subject of the e-mail is the value specified in the TITLE parameter on the OUTPUT JCL statement. If the TITLE parameter is not specified, the subject is either the title value your administrator specified in the Allocation section of the printer definition or the job name. The title in the printer definition is used only if either the resubmit for filtering function or Print Interface subsystem is used.
- The sender is the user ID of the user who ran the job.
- You can receive replies from an e-mail unless a firewall prevents the z/OS system from receiving replies from the sending system. Use the z/OS UNIX **mail** or **mailx** command to view your mail. To use these commands, your ID must be a valid z/OS UNIX user ID. For more information about these commands, see *z/OS UNIX System Services Command Reference*.

Table 4 shows the tasks related to sending output to an e-mail destination. Required tasks are required by all installations. Optional tasks are required only if the listed condition applies.

Table 4. Sending output to an e-mail destination

Task	Condition	See page
Modifying JCL to send output to an e-mail destination	Required	111
Specifying the e-mail address list in an alias file	Optional: If a z/OS UNIX sendmail alias name is specified in the printer definition	112

Modifying JCL to send output to an e-mail destination

If you currently use JCL to print output using IP PrintWay, in most cases you need to make only minimal changes to the JCL. You might need to modify these JCL parameters:

- Specify the name of the printer definition for the e-mail destination in the FSSDATA parameter on the OUTPUT statement, or specify the DEST, CLASS, and FORMS parameters that your administrator associated with the printer definition.
- If you currently specify the IP address of the printer in the DEST=IP parameter on the OUTPUT statement, remove the DEST=IP parameter. This is because you must specify the e-mail address list of the recipients, or the sendmail alias name that represents the e-mail address list, in the printer definition. You cannot currently specify the e-mail address list directly in a JCL parameter.
- Remove the RETRYL and RETRYT parameters from the OUTPUT statement, or specify values of 0, because retries are not recommended when you send output to e-mail destinations.

You can specify these optional JCL parameters to customize your e-mails:

- **TITLE** parameter: Specify the subject of the e-mail in the **TITLE** parameter on the **OUTPUT** statement.
- **DSNAME** parameter: Specify the name of the e-mail attachment in the **DSNAME** parameter on the **DD** statement.

For example, if you specify **DSNAME=&&REPORT**, the attachment name is **REPORT.pdf** or **REPORT.txt**, where the file name extension (**pdf**, **txt**) identifies the data format of the e-mail attachment. IP PrintWay automatically appends the appropriate extension to the name of the attachment.

To send output data sets that contain either AFP data or line data that requires AFP resources, all AFP resources must be included inline in the data set so that the file can be viewed with the IBM AFP Viewer. If the required AFP resources are not already inline, you can use the IBM AFP Conversion and Indexing Facility (ACIF) program, a feature of PSF for OS/390, to create a file that contains the AFP resources. Then, you can concatenate that resource file to the data file.

Related information: For examples of JCL to use when you send output to an e-mail destination, see “JCL examples” on page 144.

Specifying the e-mail address list in an alias file

Instead of specifying the e-mail address list of the recipients in the printer definition, your administrator can specify one or more alias names in the printer definition. An alias name is a name defined to z/OS UNIX sendmail that represents one or more actual e-mail addresses. For example, alias name **dept123** might represent the e-mail addresses of all employees in department 123. The alias name is specified in the printer definition. Only your administrator needs to know the alias name.

The actual e-mail address list can be defined in any UNIX file. If the file is one that you can edit, the administrator does not need to change the printer definition whenever you need to change the address list. For example, your administrator can specify that the actual e-mail address list for alias **dept123** is located in file **/u/user1/dept123.list**.

Before you begin: For each address list, your administrator must do these tasks:

- Create a printer definition and specify a sendmail alias name in the definition.
- In the sendmail aliases file **/etc/aliases**, specify the same alias name and specify the name of a file to contain the actual e-mail address list. Ask your administrator for the name of this file so that you can create it.

Steps for creating an alias file:

1. Create a file using the name defined by your administrator. For example, create file **/u/user1/dept123.list** using your preferred editor:

```
oedit /u/user1/dept123.list
```

2. Specify the e-mail addresses in this file:

```
user1@xyz.com,user2@xyz.com,user3@xyz.com,user4@xyz.com,
user5@xyz.com
```

3. Change the permissions of the file so that the file is readable by everyone but writable only by the owner:

```
chmod 755 /u/user1/dept123.list
```

-
4. Change the permissions of the directory so that it is readable and executable by everyone but writable only by the owner:

```
chmod 755 /u/user1
```

For more information about the z/OS UNIX commands used in this example, see *z/OS UNIX System Services Command Reference*.

Transforming output data

The Print Interface component of Infoprint Server, together with transforms that Infoprint Server Transforms provides, can transform data created by a batch application before writing it to the JES spool. Print Interface can transform data to a format the printer accepts or to a format suitable for viewing in an e-mail attachment.

In addition, Infoprint XML Extender for z/OS, a separate licensed IBM program product, lets you transform Extensible Markup Language (XML) files to AFP format for printing or viewing. For more information, see *Infoprint XML Extender for z/OS*.

Table 5 lists the transforms that are available with Infoprint Server Transforms and other transform products, and refers you to the section in this book that describes the functions and limitations of each transform.

Table 5. Data transforms

Transform	See page
Line data and AFP data to Printer Control Language (PCL) format	28
Line data and AFP data to Portable Data Format (PDF)	35
Line data and AFP data to PostScript format	43
PCL data to AFP format	66
PDF data to AFP format	70
PostScript data to AFP format	70
SAP Output Text Format (OTF) data to AFP format	79
SAP Advanced Business Application Programming (ABAP) data to line data	79
XML to AFP format	83

Infoprint Server provides two methods that you can use to transform and print data sets created by a batch application:

- **Print Interface subsystem:** The Print Interface subsystem can transform data created by a batch application *before* the data is written to the JES spool. The subsystem writes the transformed data to an output data set on the JES spool. The output data set on the JES spool can then be printed on any printer or sent to an e-mail destination. To use the Print Interface subsystem, you specify the SUBSYS parameter on the DD JCL statement for the output data set.
- **Resubmit for filtering function:** When your administrator enables the IP PrintWay resubmit for filtering function, Print Interface can transform data created by a batch application *after* JES has written the data to an output data set on the JES spool. After Print Interface transforms the data, it writes the transformed data

to a new output data set on the JES spool. IP PrintWay then prints the output data set or sends it to an e-mail destination. Because your administrator selects the resubmit for filtering function in the printer definition, in most cases no JCL changes are required to use this function.

Table 6 compares the advantages and limitations of the Print Interface subsystem and the resubmit for filtering function.

Table 6. Comparison of Print Interface subsystem and the resubmit for filtering function

Print submission method	Advantages	Limitations
Print Interface subsystem	<ul style="list-style-type: none"> You can use standard DD and OUTPUT JCL statements with minimal JCL changes. You can specify Infoprint Server job attributes. The data set can be printed on any printer or sent to an e-mail destination. 	<ul style="list-style-type: none"> Only one OUTPUT JCL statement for each data set is supported. DEST, HOLD, MODIFY, SEGMENT, and SYSOUT parameters on the DD JCL statement are not supported. JES2 output grouping is not supported.
Resubmit for filtering function	You can use standard DD and OUTPUT JCL statements with, in most cases, no JCL changes.	<ul style="list-style-type: none"> The data set can be sent only to a printer or e-mail destination controlled by IP PrintWay. Less efficient than the subsystem because data is written to the JES spool twice. DEST=IP, PRTQUEUE, and PORTNO parameters on the OUTPUT JCL statement are not supported. JES2 output grouping is not supported.

You can also use these methods to transform and print existing data sets:

- **AOPPRINT JCL procedure:** The AOPPRINT JCL procedure uses Print Interface to transform data in an existing MVS data set or UNIX file and to write the transformed data to an output data set on the JES spool. The output data set on the JES spool can be printed on any printer or sent to an e-mail destination. For more information, see Chapter 5, “Printing using the AOPPRINT JCL procedure” on page 153.
- **Transform commands:** The z/OS UNIX transform commands, which you can run using the AOPBATCH program, transform data in existing MVS data sets or UNIX files. The transform commands write the transformed output to an MVS data set or UNIX file but do not write the data set to an output data set on the JES spool for printing. For more information, see Chapter 6, “Transforming data with the AOPBATCH program” on page 159.

Related administrator tasks: To transform data, your administrator must:

- Customize Infoprint Server Transforms (5697–F1), the Infoprint Server Transform Manager, and any other transform products. To use the AFP to PCL, AFP to PostScript, or AFP to PDF transform, the administrator must scale 240–pel fonts to 300 pels because these transforms require 300-pel fonts.
- If you want to use the Print Interface subsystem, edit the Infoprint Server configuration file so that the subsystem starts.
- Specify the appropriate transforms in the printer definitions in the Printer Inventory. If you want to use the resubmit for filtering function, the administrator must select this function in the printer definition.

For information, see *z/OS Infoprint Server Customization* and *z/OS Infoprint Server Operation and Administration*.

Transforming data using the Print Interface subsystem

The Print Interface subsystem can transform data created by a batch application from one data format to another and then write the transformed data to an output data set on the JES spool. The output data set on the JES spool can then be printed on any printer or sent to an e-mail destination. You might want to use the Print Interface subsystem in these situations:

- To print PCL, PostScript, and PDF data on IBM AFP printers controlled by PSF for OS/390.
- To print line data and AFP data on PCL, PostScript, and PDF printers controlled by IP PrintWay.
- To send line data and AFP data in PDF format to e-mail destinations using the IP PrintWay e-mail function.
- To specify Infoprint Server job attributes.

To use the Print Interface subsystem, code these JCL parameters:

- **SUBSYS** parameter on the DD JCL statement, with these subparameters:
 - Name of the Print Interface subsystem. Ask your administrator for the subsystem name. The subsystem name is usually AOP1.
 - Name of a printer definition in the Infoprint Server Printer Inventory. Ask your administrator for the printer definition name.
 - Infoprint Server job attributes for special printing requirements. For the job attributes you can specify, see Chapter 3, “Using job attributes” on page 85.

Most of the Infoprint Server job attributes correspond to parameters on the DD and OUTPUT JCL statements. For example, the **copies** job attribute corresponds to the COPIES JCL parameter. Therefore, in most cases, specify the JCL parameters that you are familiar with and do not specify job attributes.

However, you might need to specify one of these attributes:

- The **filter-options** attribute, which lets you specify transform options. Your administrator can specify transform options in the printer definition. However, you might want to specify a different transform option for a specific data set.
 - The **document-format** attribute, which lets you specify the data format. This attribute is required only if you print data whose format Infoprint Server cannot detect.
 - The **document-codepage** attribute, which lets you specify a code page for the input data. This attribute is required only if you print data that uses a different code page than the document code page specified in the printer definition or the default document code page.
- If you code the DSNAMES parameter on the DD JCL statement, code the format that is suitable for a sysout data set: `&&dsname`.
 - Print-related parameters on the DD and OUTPUT JCL statements. Your administrator can specify default values for these JCL parameters in the printer definition. Therefore, you can omit any JCL parameters that have suitable defaults. If your administrator does not provide a default value for a JCL parameter, the standard default value applies. However, JES default values for the CHARS, UCS, PAGEDF, and FCB parameters are not used to transform data.

Limitations: These limitations apply when you use the Print Interface subsystem:

- You *cannot* use the DEST, CLASS, and FORMS parameters on the OUTPUT JCL statement to select the IP PrintWay printer definition.
- Do *not* code the SEGMENT and SYSOUT parameters on the DD JCL statement. If you do, you receive a JCL error.
- Do *not* code the DEST, HOLD, and MODIFY parameters on the DD JCL statement. The Print Interface subsystem ignores these parameters. You can, however, specify the OUTDISP parameter on the OUTPUT JCL statement instead of the HOLD parameter on the DD JCL statement.
- Specify only one OUTPUT JCL statement for each DD statement. The Print Interface subsystem uses only *one* OUTPUT JCL statement, in this order:
 1. The first OUTPUT JCL statement referred to in the OUTPUT parameter on the DD statement.
 2. The first OUTPUT JCL statement with DEFAULT=YES in the same job step.
 3. The first OUTPUT JCL statement with DEFAULT=YES in the job.
- Each output data set that the Print Interface subsystem creates on the JES spool is placed in a separate JES output subgroup from other output data sets in the same job step, regardless of the value specified in the GROUPID parameter on the OUTPUT JCL statement.
- The QSAM and BSAM access methods and the OPEN, CLOSE, and PUT functions are supported. Other access methods and functions (such as CHECKPOINT, GET, and LOCATE) are not supported.
- JES2 /*OUTPUT JCL statements and JES3 /*FORMAT JCL statements are ignored.
- If your application writes multiple output data sets that require data transforms, your job and other jobs might not complete if your administrator limits the maximum number of data transforms. Therefore, before using the Print Interface subsystem, contact your administrator to determine whether the **maximum-active** attribute in the transform configuration file is suitable for your application.

Error handling: When the Print Interface subsystem detects an error, it writes an error message to your job log, and it does not write any output data to the JES spool for the job step. If the subsystem detects an error during PUT and CLOSE operations in your application, it abnormally terminates with abend code 09B after writing an error message. Some situations that can cause an abnormal termination are:

- The printer does not support the format of the data that your application writes to the DD statement. Your administrator specifies the supported data formats in the printer definition. For information about the supported data formats, see “document-format” on page 91.
- The data transform is not installed or is not customized correctly.

Related information:

- “JCL parameters for the Print Interface subsystem” on page 139
- JCL Examples:
 - “Print line or AFP data on a PostScript printer using the Print Interface subsystem” on page 151
 - “Print PostScript, PCL, or PDF data on an IBM AFP printer using the Print Interface subsystem” on page 152

Modifying JCL to use the Print Interface subsystem

These examples show how to modify the JCL you might use to print a data set to the same printer:

Example 1: JCL that does *not* use the Print Interface subsystem

```
//DD1 DD SYSOUT=E,DEST=PRT003,DSNAME=&&MYDATA
```

Example 2: JCL that uses the Print Interface subsystem (changes in bold)

```
//DD1 DD SUBSYS=(AOP1, 'printer003'),DSNAME=&&MYDATA
```

These examples assume that printer definition printer003 in the Infoprint Server Printer Inventory contains these values:

Field	Value
CLASS	E
DEST	PRT003
FORMS	not specified (JES default value is used)

These changes were made in these JCL examples:

- In Example 2, the SYSOUT parameter on the DD JCL statement was replaced with the SUBSYS parameter. In the SUBSYS parameter, the name of the Print Interface subsystem (AOP1) and the name of the printer definition that your administrator defined for the printer (printer003) are specified.
- In Example 2, the class, destination, and forms values are not specified because the printer definition contains the same values as shown in Example 1. However, to override these values in the printer definition, you could code the CLASS, DEST, and FORMS parameters on an OUTPUT JCL statement.

Transforming data using the resubmit for filtering function

IP PrintWay, with the resubmit for filtering function enabled, can transform data in a system output (sysout) data set from one data format to another (if necessary) and then send it to a remote printer or to an e-mail destination. You might want to use the resubmit for filtering function in these situations:

- To print data sets that contain line data and AFP data on remote PCL, PostScript, and PDF printers controlled by IP PrintWay.
- To send line data and AFP data in PDF format to an e-mail destination.

To use the resubmit for filtering function, you do not need to specify any special JCL parameters. When you print a data set that contains line or AFP data, you can specify the same JCL parameters as you usually do when you print on a PSF-controlled printer. However, you must direct the data set to IP PrintWay instead of to the PSF for OS/390 printer. In the printer definition, your administrator can specify default values for some of the parameters that you can specify on the DD and OUTPUT JCL statements. Therefore, you can omit JCL parameters that have suitable defaults.

Limitations: The resubmit for filtering function has these limitations:

- Do not code the DEST=IP, PRTQUEUE, and PORTNO JCL parameters on the OUTPUT JCL statement because IP PrintWay ignores these parameters.
- JES2 output grouping is not supported. Each output data set is placed in a separate JES output subgroup, regardless of the value specified in the GROUPID parameter on the OUTPUT JCL statement.

Related information:

- “JCL parameters for transforming AFP and line data to PCL, PostScript, or PDF format” on page 130
- JCL Examples:
 - “Print line or AFP data on a PostScript or PCL printer using the resubmit for filtering function” on page 150
 - “Send line or AFP data to an e-mail destination as PDF data and print the AFP data on an AFP printer” on page 149
- *z/OS Infoprint Server Operation and Administration* contains more information about how the resubmit for filtering function works and how to select it in the printer definition

JCL parameters

This section describes JCL parameters that have special considerations when you print data sets using IP PrintWay or when you use the Print Interface subsystem. You can find detailed information about these types of JCL parameters:

JCL parameters	See page
Parameters for printing with IP PrintWay	118
Parameters for transforming AFP data and line data to PCL, PostScript, or PDF format	130
Parameters for the Print Interface subsystem	139
Parameters for distributing output	143
Parameters for printing with Infoprint Manager for AIX or Infoprint Manager for Windows	144

For more information about JCL parameters, see *z/OS MVS JCL Reference*.

JCL parameters for printing with IP PrintWay

This section describes JCL parameters that IP PrintWay uses when it sends a data set to a printer or to an e-mail destination. You can specify these JCL parameters on either the DD or OUTPUT JCL statement. If you specify the same parameter on both JCL statements, the parameter on the DD statement is used.

DD JCL Statement:

```

COPIES=nnn
DEST={(node,destination_name) | destination_name}
DSNAME=&&dataset_name
FCB=fcb_name
SYSOUT=(class,,form_name)
TITLE='description of output'

```

OUTPUT JCL Statement:

```

CLASS=class
COPIES=nnn
DEST=[{node.]destination_name | '[node.]IP:host'}]
DUPLEX={NO | NORMAL | TUMBLE}
FCB=fcb_name
FORMS=form_name
FSSDATA='printer=printer_definition_name'
NOTIFY=([node.]userid,...)
[PORTNO=port_number | PRTQUEUE='print_queue']
PRTOPTNS='component_name'
RETAINF={'hhhh:mm:ss' | FOREVER}
RETAINS={'hhhh:mm:ss' | FOREVER}
RETRYL=nnnnn
RETRYT='hhhh:mm:ss'
TITLE='description of output'

```

Figure 10. Summary of JCL parameters for all output processed by IP PrintWay

CLASS=class

Specifies the 1-character alphanumeric output class of the data set. If the Print Interface subsystem does not process the data set, IP PrintWay can use this parameter, in combination with the destination name and form name, to select a printer definition in the Printer Inventory to format and print the data set. Ask your administrator which class to specify.

Default:

- If the Print Interface subsystem processes the data set, the class in the printer definition is used. If none is specified, JES determines the default class.
- If the Print Interface subsystem does not process the data set, JES determines the default class.

Tips:

1. You can also specify the class in the SYSOUT parameter of a DD JCL statement.
2. If you specify more than one parameter that can be used to locate a printer or e-mail destination, IP PrintWay uses these priorities:
 - a. The printer's host name or IP address specified by the DEST=IP parameter
 - b. The printer's address or the e-mail address in the printer definition specified in the SUBSYS parameter
 - c. The printer's address or the e-mail address in the printer definition specified in the FSSDATA parameter

- d. The printer's address or the e-mail address specified in the printer definition that matches the values of any combination of the DEST=*destination_name*, CLASS, and FORMS parameters

Examples:

In this example, IP PrintWay uses the printer definition associated with CLASS P and DEST MYPRINT to process the data set:

```
//OUTDS  OUTPUT CLASS=P,DEST=MYPRINT
//DD1    DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

In this example, the Print Interface subsystem and IP PrintWay use the printer definition named myprinter to process the data set. CLASS=P does not affect which printer definition is used. However, the Print Interface subsystem allocates the data set on the JES spool in JES output class P and with destination name MYPRINT.

```
//OUTDS  OUTPUT CLASS=P,DEST=MYPRINT
//DD1    DD SUBSYS=(AOP1,'myprinter'),OUTPUT=(*.OUTDS)
```

COPIES=*nnn*

Specifies the number of copies you want to print, from 1 to 255.

Tips:

1. Only one copy prints when you print on VTAM-controlled printers or on Internet Printing Protocol (IPP) printers that do not support the **copies** IPP job attribute.

To print copies in these cases, specify multiple OUTPUT statements and refer to them in the OUTPUT parameter of the DD statement. For example:

```
//OUTDS1 OUTPUT FSSDATA='printer=myprinter'
//OUTDS2 OUTPUT FSSDATA='printer=myprinter'
//DD1    DD SYSOUT=P,OUTPUT=(*.OUTDS1,*.OUTDS2)
```

This work-around creates multiple output data sets on the JES spool. However, this work-around cannot be used if the Print Interface subsystem processes the data set because the subsystem ignores all but the first reference to an OUTPUT statement.

2. Group values that you specify on this parameter are ignored.
3. This parameter is ignored when you send data to an e-mail destination.
4. The administrator can limit the number of copies that you can specify. If you request more than the allowed number of copies, the data set does not print.
5. If you use the Print Interface subsystem to process the data set, you can specify up to 32640 copies in the **copies** job attribute. Specify the **copies** job attribute in the SUBSYS parameter on the DD JCL statement.

Default:

- If the Print Interface subsystem processes the data set, the number of copies in the printer definition is used. If none is specified, JES determines the default number of copies.
- If the Print Interface subsystem does not process the data set, JES determines the default number of copies.

Examples:

```
//DD1    DD      COPIES=14
//OUTDS  OUTPUT COPIES=14
```

DEST={[*node.*]destination_name | '[*node.*]IP:host'}

Specifies either the destination name or the IP address of the printer's host system.

DEST=[*node.*]destination_name

Specifies the node name and destination name of the printer's host system.

node

Specifies the 1 to 8 character node name of the printer's host system. The node name is optional. If you specify the node name in the DEST parameter on a DD JCL statement, use this format:
DEST=(*node,name*).

Default:

- If the Print Interface subsystem processes the data set, the JES node in the printer definition is used. If none is specified, JES determines the default node.
- If the Print Interface subsystem does not process the data set, JES determines the default node.

destination_name

Specifies the destination name of the printer. The name must consist of 1 to 8 alphanumeric or national (\$, #, @) characters. If the Print Interface subsystem does not process the data set, IP PrintWay can use this parameter, in combination with the class and form name, to select a printer definition to format and print the data set. Ask your administrator which destination name to specify.

Note: If you use the Print Interface subsystem, specify the DEST parameter on the OUTPUT JCL statement. The subsystem ignores the DEST parameter on the DD statement.

Examples: In these examples, IP PrintWay uses the printer definition associated with CLASS P and DEST PRT003 to process the data set:

```
//DD1 DD SYSOUT=P,DEST=PRT003
```

or

```
//OUTDS OUTPUT DEST=BOULDER.PRT003
//DD1 DD SYSOUT=P,OUTPUT=(*.OUTDS)
```

DEST='[*node.*]IP:host'

Specifies the node name and the IP address of the printer's host system.

node

Specifies the 1 to 8 character node name of the printer's host system. The node name is optional.

Default:

- If the Print Interface subsystem processes the data set, the JES node in the printer definition is used. If none is specified, JES determines the default node.
- If the Print Interface subsystem does not process the data set, JES determines the default node.

host

Specifies the 1 to 115 character IP address of the printer's host system in either of these formats (always enclose the IP keyword and value in single quotation marks):

Dotted decimal address

A series of integers in the range of 0 to 255, separated by periods (decimal address). For example:

9.99.12.85

Host name

A series of domain names that can contain alphanumeric characters and dashes (-), separated by periods (.). The first character must be alphabetic or numeric. For example:

leo.boulder.xyz.com

Default: The printer's IP address or host name in the printer definition is used.

Note: Do not enter an IP address in the colon-hexadecimal format because Infoprint Server does not currently support this format.

Examples:

```
//OUTDS OUTPUT DEST='IP:99.153.123.232'
```

```
//OUTDS OUTPUT DEST='IP:XYZ.COM'
```

```
//OUTDS OUTPUT DEST='NODE01.IP:XYZ.COM'
```

Tips:

1. JES does not use the host name or the IP address when determining whether the output data set meets its work-selection criteria. Therefore, if your administrator has defined destination as a JES work-selection criterion for IP PrintWay, specify `DEST=name` rather than `DEST=IP`. If you specify `DEST=IP`, JES will not find a match.
2. If you specify more than one parameter that can be used to locate the printer or e-mail destination, IP PrintWay uses these priorities:
 - a. The printer's host name or address specified by the `DEST=IP` parameter
 - b. The printer's address or the e-mail address in the printer definition specified in the `SUBSYS` parameter
 - c. The printer's address or the e-mail address in the printer definition specified in the `FSSDATA` parameter
 - d. The printer's address or the e-mail address in the printer definition that matches the values of any combination of the `DEST=name`, `CLASS`, and `FORMS` parameters
3. If you specify a printer definition name in the `FSSDATA` or `SUBSYS` parameter and the printer definition does not specify the LPR or direct sockets printing protocol, IP PrintWay ignores the `DEST=IP` parameter.
4. Use the same method to identify the host system, either the host name or the IP address, in all references to the host system. Also, use the same lower and uppercase characters. This ensures that data sets transmitted to the same printer are transmitted in the correct order.
5. If the resubmit for filtering function is used, do not specify the `DEST=IP` parameter because IP PrintWay ignores it and instead uses the IP address in the printer definition.

DSNAME=&&dataset_name

Specifies the data set name to assign to the sysout data set. The z/OS system generates a qualified name for the sysout data set and uses the value you specify in the `DSNAME` parameter as the last qualifier in the name.

Begin the name with two ampersands (&&). Follow the ampersands with 1 to 8 alphanumeric or national (\$, #, @) characters, a hyphen, or a character X'C0'. The first character after the ampersands must be alphabetic or national (\$, #, @).

Recommendations: Specify a DSNNAME parameter so that you can identify printed output more easily and to give a meaningful name to an e-mail attachment:

- The fully qualified data set name can be printed on page headers and on separator pages. Therefore, if you specify the DSNNAME parameter, you can identify your output more easily. Whether a header or separator page prints depends on the IP PrintWay options your administrator has selected in the printer definition and how your administrator has configured the printer's separator page.
- If the resubmit for filtering function is used, the value you specify in the DSNNAME parameter is also the last qualifier of the data set name of the *second* data set that Infoprint Server dynamically allocates on the JES spool while processing the data. Therefore, if you specify the DSNNAME parameter, you can locate this second data set on the JES spool more easily.
- When IP PrintWay sends the data to an e-mail destination, the value you specify in the DSNNAME parameter is used as the name of the e-mail attachment. If you do not specify this parameter, IP PrintWay uses the job name as the name of the e-mail attachment.

Default: The last qualifier of the fully qualified data set name is a question mark (?).

Example:

```
//DD1 DD SYSOUT=P,DSNNAME=&&FEBSALES
```

The z/OS system generates a data set name such as:

```
userid.jobname.jobid.Ddsnumber.FEBSALES
```

FEBSALES is the last qualifier of the fully qualified name of the second data set that Print Interface allocates on the JES spool when the resubmit for filtering function is used.

FEBSALES is the name of the e-mail attachment that IP PrintWay sends to an e-mail destination.

FCB=*fcf_name*

Specifies the 1 to 4 character name of the forms control buffer (FCB) member of the SYS1.IMAGELIB library.

IP PrintWay searches the library first for FCB4*fcf_name*, then FCB2*fcf_name*, then FCB3*fcf_name* unless you are printing to a VTAM-controlled printer. In this case, IP PrintWay searches the SYS1.IMAGELIB library only for FCB2*fcf_name*.

IP PrintWay can use the FCB to format the data. However, the administrator must select the IP PrintWay **Use FCB** formatting option in the printer definition. For more information about FCB processing, see *z/OS Infoprint Server Operation and Administration*.

Default:

- If the Print Interface subsystem processes the data set, the FCB in the printer definition is used. If none is specified, JES determines the default FCB.

- If the Print Interface subsystem does not process the data set, JES determines the default value. If JES does not provide a default value and the resubmit for filtering function is used, the FCB in the printer definition is used.
- The administrator can specify a default FCB name to JES in the JES initialization member of SYS1.PARMLIB.

Examples:

```
//DD1 DD FCB=STD2
//OUTDS OUTPUT FCB=STD2
```

FORMS=*form_name*

Specifies the 1 to 8 character form name. If the Print Interface subsystem does not process the data set, IP PrintWay can use this parameter, in combination with the class and destination name, to select a printer definition to format and print the data set. Ask your administrator which form name to specify.

Tips:

1. You can also specify the form name in the SYSOUT parameter of a DD JCL statement.
2. If you specify more than one parameter that can be used to locate a printer or e-mail destination, IP PrintWay uses these priorities:
 - a. The printer's host name or address specified by the DEST=IP parameter
 - b. The printer's address or the e-mail address in the printer definition specified in the SUBSYS parameter
 - c. The printer's address or the e-mail address in the printer definition specified in the FSSDATA parameter
 - d. The printer's address or the e-mail address in the printer definition that matches the values of any combination of the DEST=*name*, CLASS, and FORMS parameters
3. The administrator can limit the values that you can specify in this parameter. If you specify a value that is not allowed, the data set might not print.

Default:

- If the Print Interface subsystem processes the data set, the form name in the printer definition in the Printer Inventory is used. If none is specified, JES provides a default form name.
- If the Print Interface subsystem does not process the data set, JES provides a default form name.

Example:

```
//OUTDS OUTPUT FORMS=WIDE
```

FSSDATA='printer=*printer_definition_name***'**

Specifies the 1 to 17 character name of the printer definition in the Printer Inventory.

Enter the **printer** subparameter in *lowercase*. The printer definition name is case-sensitive. Enter it exactly as the name is specified in the Printer Inventory.

If you specify more than one parameter that can be used to locate a printer or e-mail destination, IP PrintWay uses these priorities:

1. The printer's host name or address specified by the DEST=IP parameter
2. The printer's address or the e-mail address in the printer definition specified in the SUBSYS parameter

3. The printer's address or the e-mail address in the printer definition specified in the FSSDATA parameter
4. The printer's address or e-mail address in the printer definition that matches the values of any combination of the DEST=*name*, CLASS, and FORMS parameters

The printer definition named in the SUBSYS parameter overrides the printer definition name in this parameter.

Default:

- If the Print Interface subsystem processes the data set and no printer definition is named in the SUBSYS parameter, the Infoprint Server default printer definition is used.
- If the Print Interface subsystem does not process the data set:
 - If the DEST=IP parameter is specified, the IP PrintWay default printer definition is used.
 - If the DEST=IP parameter is not specified, the printer definition that matches the class, destination, and forms name is used.

Example:

```
//OUTDS OUTPUT FSSDATA='printer=Printer5'
```

NOTIFY=([*node.*]userid,...)

Specifies up to 4 user IDs that are notified when the data set has been successfully or unsuccessfully transmitted. Separate the user IDs with commas.

node

Specifies a 1 to 8 character node name. The node name is optional.

userid

Specifies a 1 to 8 character user ID.

IP PrintWay notifies the users when the transmission is successful, when the transmission fails, or when IP PrintWay deletes the data set from the JES spool.

Default: If either the Print Interface subsystem processes the data set or the resubmit for filtering function is used, the notify values in the printer definition apply. Otherwise, no users are notified.

Example:

```
//OUTDS OUTPUT NOTIFY=(SEATTLE.JOE,SEATTLE.MARY)
```

PORTNO=port_number

Specifies the number of the port to use for a direct socket printing connection. The valid range is 100 to 65535.

IP PrintWay uses the number of the port specified in this parameter instead of the port number in the printer definition.

Tips:

1. Do not code both PORTNO and PRTQUEUE.
2. If you code DEST=IP, also code either PRTQUEUE or PORTNO.
3. If the printer definition does not specify the direct sockets printing protocol, IP PrintWay ignores this parameter.

4. If you code DEST=IP and PORTNO but do not specify a printer definition name in either the FSSDATA or SUBSYS parameter, IP PrintWay uses the direct sockets printing protocol to transmit the data to the specified port number.
5. If the resubmit for filtering function is used, do not code PORTNO because IP PrintWay ignores it and instead uses the port number specified in the printer definition.

Default: The printer's port number in the printer definition is used.

Example:

```
//OUTDS OUTPUT PORTNO=2501
```

PRTOPTNS='component_name'

Specifies the 1 to 16 character name of one or more *components* that contain printing options you want IP PrintWay to use. Ask your administrator for the name of components suitable for your data set. The component name is case-sensitive. Enter it exactly as the components are defined in the Printer Inventory. If the name contains special characters (such as a dash) or lowercase letters, enclose the name in single quotation marks.

A component is an entity in the Printer Inventory. IP PrintWay uses printing options specified in these three types of components: Processing, IP PrintWay Options, and Protocol. If more than one type of component exists with the specified name, IP PrintWay uses options specified in all of the components with the specified name. If a component of one of the three types does not exist, IP PrintWay uses default values for the printing options that can be specified in the missing component.

IP PrintWay uses only a subset of all options that can be specified in these components. IP PrintWay ignores other options specified in these components and instead uses the options specified in the printer definition. Some of the options that IP PrintWay uses from components are:

- Whether to use the FCB to format the data set
- How many lines to print on a page
- Whether to print a header on each page
- Whether to translate a data set from EBCDIC to ASCII
- Whether to transmit multiple data sets in a job at the same time
- Which installation-written exit routines to use

For more information about which options IP PrintWay uses from components and about how to define components for use with the PRTOPTNS parameter, see *z/OS Infoprint Server Operation and Administration*.

Note: If the resubmit for filtering function is used, do not specify the PRTOPTNS parameter. IP PrintWay ignores it and instead uses options specified in the printer definition.

Default: IP PrintWay determines the default printing options:

1. The options specified in the printer definition are used.
2. For options not specified in the printer definition, IP PrintWay uses hard-coded default values.

Example:

```
//OUTDS OUTPUT PRTOPTNS='PostScript'
```

PRTQUEUE='print_queue'

Specifies the 1 to 127 character alphanumeric name of the target print queue.

This parameter might be case-sensitive. For example, on UNIX systems, lp0 and LP0 refer to different print queues. If the name contains special characters (such as a dash) or lowercase letters, enclose the name in single quotation marks.

IP PrintWay uses the print queue specified in this parameter instead of the print queue name in the printer definition.

Tips:

1. Do not code both PORTNO and PRTQUEUE.
2. If you code DEST=IP, also code either PRTQUEUE or PORTNO.
3. If the printer definition does not specify the LPR printing protocol, IP PrintWay ignores this parameter.
4. If you code DEST=IP and PRTQUEUE parameter, but do not specify a printer definition name in either the FSSDATA or SUBSYS parameter, IP PrintWay uses the LPR printing protocol to transmit the data to the specified print queue.
5. If the resubmit for filtering function is used, do not code PRTQUEUE because IP PrintWay ignores it and instead uses the print queue name specified in the printer definition.

Default: The print queue name in the printer definition is used.

Example:

```
//OUTDS OUTPUT PRTQUEUE='lpd0'
```

RETAINF={'hhhh:mm:ss' | FOREVER }

Specifies the period of time for which IP PrintWay retains the data set on the JES queue after a transmission fails and all requested retries have been attempted.

Specify the time in the format *hhhh:mm:ss*:

hhhh is the number of hours (range 0 to 9999)

mm is the number of minutes (range 0 to 59)

ss is the number of seconds (range 0 to 59)

You can omit zeroes and colons to the left of the significant portion of the time value. Enclose the entire value in single quotation marks.

To retain data sets forever, enter FOREVER. In this case, IP PrintWay never automatically deletes failed data sets from the JES spool. The operator must delete the data set from the JES spool or retransmit the data set.

IP PrintWay uses the retention value specified in this parameter instead of the value in the printer definition.

Note that the retention period for failed transmissions is separate from the retry limit and time. The retention period indicates the amount of time that IP PrintWay retains data sets on the JES spool *after* the last retry fails.

Default: IP PrintWay determines the default value:

1. The retain value in the printer definition is used.
2. No retention.

Examples:

- This OUTPUT statement specifies that IP PrintWay should retain the data set on the JES spool for 48 hours:

```
//OUTDS OUTPUT RETAINF='48:00:00'
```

- This OUTPUT statement specifies that IP PrintWay should retain the data set on the JES spool until the administrator deletes it or retransmits it:

```
//OUTDS OUTPUT RETAINF=FOREVER
```

RETAINS={'*hhhh:mm:ss*' | FOREVER}

Specifies the period of time for which IP PrintWay retains the data set on the JES queue after a successful transmission.

Specify the time in the format *hhhh:mm:ss*:

hhhh is the number of hours (range 0 to 9999)

mm is the number of minutes (range 0 to 59)

ss is the number of seconds (range 0 to 59)

You can omit zeroes and colons to the left of the significant portion of the time value. Enclose the entire value in single quotation marks.

To retain data sets forever, enter FOREVER. In this case, IP PrintWay ever automatically deletes successfully transmitted data sets from the JES spool. The administrator must delete the data set from the JES spool.

IP PrintWay uses the retention time specified in this parameter instead of the value in the printer definition.

Note that the retention period for successful transmissions is separate from the retry limit and time. The retention period indicates the amount of time that IP PrintWay retains data sets on the JES spool *after* transmission succeeds.

Default: IP PrintWay determines the default value:

1. The retain value in the printer definition is used.
2. No retention.

Examples:

- This OUTPUT statement specifies that IP PrintWay should retain the data set on the JES spool for 4 hours:

```
//OUTDS OUTPUT RETAINS='04:00:00'
```

- This OUTPUT statement specifies that IP PrintWay should not retain the data set on the JES spool:

```
//OUTDS OUTPUT RETAINS='0'
```

RETRYL=*nnnnn*

Specifies the maximum number of times that IP PrintWay is to retry an unsuccessful transmission. Specify a number from 0 to 32767.

IP PrintWay uses the retry limit specified in this parameter instead of the retry limit in the printer definition.

Recommendations:

- When you send the output data set to an e-mail destination, omit both the RETRYL and RETRYT parameters.
- Do not specify this parameter so that the value your administrator specifies in the printer definition is used. The value you specify can affect IP PrintWay performance.

Default: The retry value in the printer definition is used. If none is specified, see Table 7.

Example:

```
//OUTDS OUTPUT RETRYL=10
```

Table 7. How retry limit and retry time work together

Retry limit	Retry time	IP PrintWay action
Blank or 0	Any value	IP PrintWay does not retry the transmission.
>0	Blank or 0	IP PrintWay retries the transmission the specified number of times.
>0	>0 but <5 seconds	IP PrintWay retries the transmission the specified number of times at the specified interval.
>0	≥5 seconds	IP PrintWay retries the transmission one time immediately, then the specified number of times at the specified interval.

RETRYT='hhhh:mm:ss'

Specifies the time interval between attempts to retransmit an unsuccessful transmission.

Specify the retry time in the format *hhhh:mm:ss*:

hhhh is the number of hours (range 0 to 9999)

mm is the number of minutes (range 0 to 59)

ss is the number of seconds (range 0 to 59)

You can omit zeroes and colons to the left of the significant portion of the time value. Enclose the retry time in single quotation marks.

IP PrintWay uses the retry time specified in this parameter instead of the retry time in the printer definition.

Recommendations:

- When you send the output data set to an e-mail destination, omit both the RETRYL and RETRYT parameters.
- Do not specify this parameter so that the value your administrator specifies in the printer definition is used. The value you specify can affect IP PrintWay performance.

Default: The retry value in the printer definition is used. If none is specified, see Table 7.

Examples: These examples both specify that IP PrintWay should retry one time immediately, then wait 1 minute between subsequent retries:

```
//OUTDS OUTPUT RETRYT='0000:01:00'
```

or

```
//OUTDS OUTPUT RETRYT=1:00
```

SYSOUT=(class,,form_name)

Specifies the class and the form name.

class

Specifies a 1 character alphanumeric class.

form_name

Specifies a 1 to 4 character form name.

You can also specify the output class and the form name in the CLASS parameter and FORMS parameter of an OUTPUT statement. To specify a form name longer than 4 characters, you *must* use the FORMS parameter of an OUTPUT statement.

Note: You must code either the SYSOUT or SUBSYS parameter, but do not code both parameters.

Example:

```
//DD1 DD SYSOUT=(P,,WIDE)
```

TITLE=*'description of output'*

Describes the output. This value can be printed on an IP PrintWay separator page or on a separator page (banner page) written by the printer's LPD. Whether this value prints on a separator page depends on how your administrator has configured the separator page or how the LPD is implemented. If the output data set is sent to an e-mail destination, this value is the subject of the e-mail.

Specify 1 to 60 EBCDIC text characters. If the description contains spaces, special characters, or lowercase characters, enclose the value in quotation marks.

Recommendation: In a JES2 environment, if you want multiple output data sets in the same job step to be sent in the same e-mail, specify the TITLE parameter with exactly the same value for all output data sets.

Default:

- For a separator page created by an IP PrintWay exit: If the resubmit for filtering function is used or if the Print Interface subsystem processes the data set, the default value is the title specified in the Allocation section of the printer definition in the Printer Inventory. Otherwise, there is no default value.
- For the LPD's separator page: If the resubmit for filtering function is used or if the Print Interface subsystem processes the data set, the default value is the title specified in the Allocation section of the printer definition in the Printer Inventory. Otherwise, the default value is the title or filename your administrator specified in the Protocol section of the printer definition. If none is specified, the default value is the fully qualified data set name.
- For the subject of an e-mail: If the resubmit for filtering function is used or if the Print Interface subsystem processes the data set, the default value is the title specified in the printer definition in the Printer Inventory. Otherwise, the default subject is the job name.

Example:

```
//OUTDS OUTPUT TITLE='Annual Report'
```

JCL parameters for transforming AFP and line data to PCL, PostScript, or PDF format

This section describes JCL parameters that the AFP to PCL, AFP to PDF, and AFP to PostScript transforms use. These parameters apply to AFP or line data jobs that Print Interface automatically transforms from line data or AFP data to another format.

The parameters are summarized in Figure 11. All parameters are optional.

DD JCL Statement:

CHARS=(*font_name1*[,*font_name2*][,*font_name3*][,*font_name4*])
UCS=*font_name*

OUTPUT JCL Statement:

CHARS=(*font_name1*[,*font_name2*][,*font_name3*][,*font_name4*])
DUPLEX={NO | NORMAL | TUMBLE}
FORMDEF=*form_definition_name*
INTRAY=*nnn*
OFFSETXB=*nnnn*[.*mmm*]*unit*
OFFSETXF=*nnnn*[.*mmm*]*unit*
OFFSEYB=*nnnn*[.*mmm*]*unit*
OFFSEYF=*nnnn*[.*mmm*]*unit*
OUTBIN=1-65 535
OVERLAYB=*overlay_name*
OVERLAYF=*overlay_name*
PAGEDEF=*page_definition_name*
PRMODE={SOSI1 | SOSI2 | SOSI3}
TRC={YES | NO}
UCS=*font_name*
USERLIB=('library_name[,...])

Figure 11. Summary of JCL parameters for all line and AFP output to be transformed to PCL, PostScript, or PDF format

In most cases, transforms interpret the parameters in the same way as PSF for OS/390 does, so that you can use the same JCL that you use when the output is printed on IBM AFP printers. These parameters have different characteristics when used with these transforms:

- **CHARS:** If the page definition used to print the job is the system default page definition and the page definition specifies a font, the transforms do not use the font specified in the CHARS parameter. Instead, the transforms use the font in the page definition. PSF for OS/390, on the other hand, uses the font specified in the CHARS parameter.
- **INTRAY:** The transforms use default input tray 1. PSF for OS/390, on the other hand, uses the printer's default source.

The parameters you can specify are:

CHARS=(*font_name1*[,*font_name2*][,*font_name3*][,*font_name4*])

Specifies the 4-character member name of the coded font that you want to use to print a data set that contains line data. You can specify up to four fonts.

font_name

Specifies the name of a coded font (in a font library) containing 4 or fewer characters, not including the prefix.

Tip: Some coded fonts have 6-character names, not counting the prefix. For these coded fonts, see *IBM AFP Fonts: Font Summary for AFP Font Collection* for the 4-character alternate coded font name.

When you use CHARS to specify the member name, do not include the 2-character prefix of the coded-font name (X0 through XG).

Coded fonts that can be used with the CHARS parameter are supplied with the IBM AFP Font Collection. The fonts you specify must reside in a font library assigned to the transform in the transform configuration file or in a user library specified with the USERLIB JCL parameter, or else they must be inline with the data set. For details about available fonts and the naming conventions, see *IBM AFP Fonts: Font Summary for AFP Font Collection*.

If you specify more than one font with the JCL CHARS parameter, you must use the TRC parameter to tell these transforms which font to use for each line of data.

Raster fonts are used unless the administrator has requested font mapping to outline fonts and your font name is in the font mapping table.

If the page definition specifies fonts, the transforms ignore the CHARS parameter.

Default: The transforms use the first value found in this order:

1. The font specified in the page definition
2. The font specified in the UCS JCL parameter
3. The font specified in the printer definition
4. The default font supplied by JES, but only if the Print Interface subsystem does not process the data set
5. The font specified in the Infoprint Server transform configuration file
6. Font X060D9

Examples:

```
//DD1 DD CHARS=(GT10,GT12)
```

or

```
//OUTDS OUTPUT CHARS=(GT10,GT12)
```

DUPLEX={NO | NORMAL | TUMBLE}

Specifies whether printing is to be done on both sides of each sheet.

NO The job is printed only on the front side of each sheet.

NORMAL

The job is printed on both sides of the sheet so that the top of side 1 is the top of side 2 (for side binding).

TUMBLE

The job is printed on both sides of the sheet so that the top of side 1 is the bottom of side 2 (for top binding).

Tip: The administrator can limit the value that you can specify in this parameter. If you specify a value that is not allowed, the data set might not print.

Default: The transforms use the first value found in this order:

1. The duplex option specified in the printer definition
2. The duplex option specified in the form definition

Example:

```
//OUTDS OUTPUT DUPLEX=NORMAL
```

FORMDEF=*form_definition_name*

Specifies the member name (from 1 to 6 alphanumeric or national characters) of the form definition you want to use. Omit the system prefix, F1, from the name. These transforms add F1 to the member name you specify.

You can store the form definition that you use in any of these places:

- In a system library assigned to these transforms
- In a user library referred to in the printer definition
- In a user library referred to in your JCL
- Inline in the print data set

Using form definitions from a user library: You can instruct these transforms to select a form definition from your user library rather than from a system library assigned to these transforms. To use a form definition from a user library:

- Refer to the user library containing the form definition in your JCL. For details, see the USERLIB parameter.
- Specify the name of the form definition in the JCL FORMDEF parameter.

Using inline form definitions: To use an inline form definition:

- Include the inline form definition in the print data set.
- If you specify the FORMDEF parameter, make sure that the name of the inline form definition matches the form definition name that you specified, or else specify FORMDEF=DUMMY. If you do not specify the FORMDEF parameter, these transforms select the first inline form definition in the print data set.
- Make sure that the data set is identified as containing carriage control characters.

You can include more than one inline form definition in a print data set, and you can change the form definition name in the JCL for different printing jobs to test different form definitions. If the name of an inline form definition does not match the FORMDEF name specified in the JCL, these transforms use the form definition from the resource library that matches the name in the JCL.

Default: The transforms use the first value found in this order:

1. The form definition specified in the printer definition
2. The first inline form definition
3. The form definition specified in the Infoprint Server transform configuration file
4. Form definition F1CP0111

Example: To specify F1USER10 as the form definition, enter:

```
//OUTDS OUTPUT FORMDEF=USER10
```

INTRAY=nnn

Specifies the one to three decimal digit number from 1 to 255 that identifies the tray from which paper is to be selected. These transforms map this tray number to the tray number of the PCL or PostScript printer, using tray-mapping values specified by the administrator in the transform configuration file. For more information about tray mapping, see “input-tray-number” on page 96.

The value you specify for this attribute overrides any input tray selection in the AFP data stream or in the form definition.

Default: The transforms use the first value found in this order:

1. The input tray specified in the printer definition
2. The input tray selected in the AFP data stream
3. The input tray specified in the form definition
4. Tray 1

Example:

```
//OUTDS OUTPUT INTRAY=4
```

OFFSETXB=nnnn[.mmm]unit

Specifies the X offset of the logical page origin to the right of the physical page origin on the back side of a double-sided sheet.

For unit, specify one of these units:

Unit	Meaning
IN	Specifies a unit of inches
CM	Specifies a unit of centimeters
MM	Specifies a unit of millimeters
PELS	Specifies a unit of picture elements (1/240 inch)
POINTS	Specifies a unit of points (1/72 inch)

Note: If you specify the unit as PELS or POINTS, you must specify the value as a whole number with no decimal point.

Default: The transforms use the first value found in this order:

1. The offset specified in the printer definition
2. The offset specified in the form definition

OFFSETXF=nnnn[.mmm]unit

Specifies the X offset of the logical page origin to the right of the physical page origin on the front of the sheet.

For unit, specify one of these:

IN	Specifies a unit of inches
CM	Specifies a unit of centimeters
MM	Specifies a unit of millimeters
PELS	Specifies a unit of picture elements (1/240 inch)
POINTS	Specifies a unit of points (1/72 inch)

Note: If you specify the unit as PELS or POINTS, you must specify the value as a whole number with no decimal point.

Default: The transforms use the first value found in this order:

1. The offset specified in the printer definition
2. The offset specified in the form definition

OFFSETYB=nnnn[.mmm]unit

Specifies the Y offset of the logical page origin below the physical page origin on the back side of a double-sided sheet.

For unit, specify one of these:

IN Specifies a unit of inches

CM Specifies a unit of centimeters

MM Specifies a unit of millimeters

PELS Specifies a unit of picture elements (1/240 inch)

POINTS

Specifies a unit of points (1/72 inch)

Note: If you specify the unit as PELS or POINTS, you must specify the value as a whole number with no decimal point.

Default: The transforms use the first value found in this order:

1. The offset specified in the printer definition
2. The offset specified in the form definition

OFFSETYF=nnnn[.mmm]unit

Specifies the offset in the Y direction of the logical page origin below the physical page origin on the front of the sheet.

For unit, specify one of these:

IN Specifies a unit of inches

CM Specifies a unit of centimeters

MM Specifies a unit of millimeters

PELS Specifies a unit of picture elements (1/240 inch)

POINTS

Specifies a unit of points (1/72 inch)

Note: If you specify the unit as PELS or POINTS, you must specify the value as a whole number with no decimal point.

Default: The transforms use the first value found in this order:

1. The offset specified in the printer definition
2. The offset specified in the form definition

Example: This example sets the page origin to .5 inches, 1.1 inches on the front side, and 1.5 inches, 1.1 inches on the back side:

```
//OUTDS OUTPUT OFFSETXF=0.5IN,OFFSETYF=1.1IN,  
//          OFFSETXB=1.5IN,OFFSETYB=1.1IN
```

OUTBIN=1-65 535

Specifies the 1- to 5-decimal-digit identifier of the output bin into which

Infoprint Server will place a print job. If the printer does not support the selection of an output bin, the job is stacked in the default output bin for the printer.

When you print on a PCL or PostScript printer, instead of on an AFP printer, specify the output bin number of the PCL or PostScript printer. The value you specify for this parameter overrides any output bin that the form definition specifies.

Default: The transforms use the first value found in this order:

1. The output bin specified in the printer definition
2. The output bin selected in the AFP data stream
3. The output bin specified in the form definition

Example:

```
//OUTDS OUTPUT OUTBIN=4
```

OVERLAYB=*overlay_name*

Specifies the member name (from 1 to 8 alphanumeric or national characters) of a medium overlay to be placed on the back side of each sheet in a two-sided job, in addition to overlays from other sources. Specify the complete name of the overlay member because these transforms do not add an O1 prefix.

Default: The transforms use the first value found in this order:

1. The overlay specified in the printer definition
2. The overlay specified in the form definition

OVERLAYF=*overlay_name*

Specifies the member name (from 1 to 8 alphanumeric or national characters) of a medium overlay to be placed on the front side of each sheet, in addition to overlays from other sources. Specify the complete name of the overlay member because these transforms do not add an O1 prefix.

Default: The transforms use the first value found in this order:

1. The overlay specified in the printer definition
2. The overlay specified in the form definition

Example: This example requests overlay O1FOVLY be placed on the front side of each sheet and overlay O1BOVLY be placed on the back side of each sheet:

```
//OUTDS OUTPUT OVERLAYF=O1FOVLY,OVERLAYB=O1BOVLY
```

PAGEDEF=*page_definition_name*

Specifies the member name (from 1 to 6 alphanumeric or national characters) of the page definition you want to use. When you specify the name in the JCL, omit the system prefix, P1. These transforms add it automatically.

If a PAGEDEF parameter is not coded in your JCL, these transforms use the page definition specified in the printer definition. If no form definition is specified in the printer definition, these transforms use the form definition in the Infoprint Server transform configuration file.

You can store the page definition that you use in any of these places:

- In a system library assigned to these transforms
- In a user library referred to in the printer definition
- In a user library referred to in your JCL

- Inline in the print data set

Using page definitions from a user library: You can instruct these transforms to select a page definition from your user library rather than from a system library assigned to these transforms. To use a page definition from a user library:

- Include in your JCL a reference to the user library that contains the page definition.
- Specify the name of the page definition in the JCL PAGEDDEF parameter of your JCL.

Using inline page definitions: To use an inline page definition:

- Include the inline page definition in the print data set.
- If you specify the PAGEDDEF parameter, make sure that the name of the inline page definition matches the name of the page definition name that you specified, or else specify PAGEDDEF=DUMMY.
- If you do not specify the PAGEDDEF parameter, these transforms select the first inline page definition in the print data set, unless a JES default page definition exists.
- If a page definition resource is included inline with the data, make sure to identify the data set as containing carriage control characters.

You can include more than one inline page definition in a print data set, and you can change the page definition name in the JCL on different printing jobs to test different page definitions. If, however, the name of an inline page definition does not match the PAGEDDEF name specified in the JCL, these transforms use the page definition from the resource library that matches the name in the JCL.

Default: The transforms use the first value found in this order:

1. The page definition specified in the FCB parameter
2. The page definition specified in the printer definition
3. The FCB value specified in the printer definition
4. The default page definition supplied by JES, but only if the Print Interface subsystem does not process the data set
5. The first inline page definition
6. The page definition specified in the Infoprint Server transform configuration file
7. Page definition P1P08682

Example: In this example, P1USER10 is the page definition name:

```
//OUTDS OUTPUT PAGEDDEF=USER10
```

PRMODE={SOSI1| SOSI2 | SOSI3}

Specifies the type of data in the print data set and whether these transforms must do optional processing of the data.

SOSI1

Specifies that each shift-out, shift-in code is to be converted to a blank and a Set Coded Font Local text control.

SOSI2

Specifies that each shift-out, shift-in code is to be converted to a Set Coded Font Local text control.

SOSI3

Specifies that the shift-in code is to be converted to a Set Coded Font Local text control and two blanks. A shift-out code is to be converted to a Set Coded Font Local text control.

JES uses values in the PRMODE parameter for job routing. These transforms ignore all values except SOSI1, SOSI2, and SOSI3, which they use to format data sets that contain both single-byte and double-byte fonts.

When you use the SOSI process, remember that:

- For the process to work correctly, you must specify two fonts in the CHARS parameter or in a page definition font list. The first font must be the single-byte font, and the second font must be the double-byte font.
- IBM recommends that you do not mix SOSI codes and TRCs in the same job.

Default:

- If the Print Interface subsystem processes the data set, the value in the printer definition is used. If none is specified in the printer definition, JES provides a default value. However, the transforms do not use the JES default value.
- If the Print Interface subsystem does not process the data set, JES provides a default value.

Example:

```
//OUTDS OUTPUT CHARS=(font_name1,font_name2),PRMODE=SOSI1
```

TRC={YES|NO}

Specifies whether the print data set contains table reference characters (TRCs).

In line data, you can use different fonts on different lines of a file by specifying TRCs at the beginning of each line after the carriage control characters, if any are present.

Examples:

```
//OUTDS OUTPUT CHARS=(GT10,GT12),TRC=YES
//DD2 DD CHARS=(GT10,GT12),DCB=OPTCD=J
```

When you use table reference characters, remember that:

- If the TRC=YES and the page definition does not identify fonts, you must specify fonts with the CHARS parameter.
- The order in which the fonts are specified in the CHARS parameter establishes which number is assigned to each associated TRC. For example, the TRCs for the fonts in the preceding example are zero for *font_name1* and one for *font_name2*.
- If you do not specify TRC=YES, but your line data contains a TRC as the first character of each line (or the second character if carriage control characters are used), the TRC is not used as a font identifier, but is printed as a text character.
- IBM recommends that you do not mix SOSI codes and TRCs in the same job.

UCS=*font_name*

Serves as another way to select a font. When a CHARS parameter is not

specified, you can specify the universal character set (UCS) parameter to select one font. If the page definition specifies a font, the UCS parameter is ignored.

Example:

```
//DD1 DD UCS=GT10
```

USERLIB=(*library_name*[,...])

Specifies the name of 1 to 8 cataloged MVS data sets (user libraries) containing AFP resources for processing the data set. The transforms dynamically allocate these data sets and search for resources in them in the order specified on the USERLIB statement. If the transforms find no resources, they search the system libraries defined in the Infoprint Server transform configuration file. The libraries you specify can contain any AFP resources: fonts, page segments, overlays, page definitions, form definitions, or object container resources.

Note: For the transforms to use these libraries, the libraries must have RACF universal read access.

Default: The transforms use the first value found in this order:

1. Resource libraries specified in the printer definition
2. Resource libraries specified in the Infoprint Server transform configuration file or, if no library is specified, a hard-coded default resource library

Example: In this example, the USERLIB parameter tells the transforms to search the libraries specified for AFP resources.

```
//OUTDS OUTPUT USERLIB=('USER.IMAGES','USER.AFP.RESOURCES')
```

JCL parameters for the Print Interface subsystem

This section describes how to code the SUBSYS JCL parameter to request that the Print Interface subsystem process a data set. It also describes the parameters of the DD and OUTPUT JCL statements that apply when you use the Print Interface subsystem.

DD JCL Statement:

SUBSYS=(*subsystem_name*[,['*printer_definition_name*'][,'*attribute=value ...*']])

Figure 12. SUBSYS parameter for the Print Interface subsystem

SUBSYS=(*subsystem_name*[,['*printer_definition_name*'][,'*attribute=value ...*']])

Specifies that the Print Interface subsystem is to process this data set.

The Print Interface subsystem supports these positional subparameters:

subsystem_name

Specifies the name of the Print Interface subsystem. This name must be the same as the Inventory name that is specified in the Infoprint Server configuration file. The Printer Inventory name is usually AOP1.

Default: None.

'printer_definition_name'

Specifies the name of the printer definition in the Printer Inventory that the

subsystem uses to process the data set. This name is case-sensitive. If the name includes any lowercase characters or special characters, enclose the name in single quotation marks. If you want to omit this parameter, but still specify job attributes, code a comma to indicate the printer definition name is omitted.

Default: The first printer definition name found, using this order:

1. The printer definition name specified in the FSSDATA parameter on the OUTPUT JCL statement.
2. The Infoprint Server default printer definition. The name of the Infoprint Server default printer definition is specified in the Printer Inventory. The default name is 1p1.

'attribute=value ...'

Specifies Infoprint Server job attributes that the subsystem uses to process and print the data set. For a list of valid job attributes, see Chapter 3, "Using job attributes" on page 85.

Rules:

- Attribute names and values are case-sensitive. All attribute names are lowercase.
- Enclose the entire list of job attributes in single quotation marks.
- Separate job attributes with one or more spaces.
- If an attribute value contains blanks or special characters, enclose that attribute value in double quotation marks.
- You can specify up to 120 characters of job attributes.
- To continue the SUBSYS parameter on another line, end the first line with a comma at the end of a complete subparameter.
- If you cannot fit all job attributes on one line, see *z/OS MVS JCL Reference* for information about how to continue a parameter field enclosed in apostrophes.

Tip: If you want to specify more than 120 characters of job attributes, instead, specify the JCL parameter that corresponds to the job attribute. For example, specify the COPIES JCL parameter instead of the **copies** job attribute. Or, specify the job attributes in an attributes file.

Overrides: Job attributes override values specified in corresponding parameters of the DD and OUTPUT JCL statements. For a list of job attributes and their corresponding JCL parameters, see Appendix B, "JCL parameters and corresponding job attributes" on page 195.

Using an attributes file: You can store attributes and values in an MVS data set or in a UNIX file (such as an HFS file). Follow these rules:

- Specify the MVS data set name or UNIX file name from which attributes are to be read in the attribute called **attributes**.
- If attributes are in an MVS data set, specify the fully qualified MVS data set name, and code four single quotation marks before the data set name and four single quotation marks after it.
- Because Print Interface must be able to read the attributes data set, give the MVS data set RACF universal read access and set the UNIX file permissions to let everyone read the file.
- For information about how to specify the attributes in the attributes file, see "Attributes files" on page 86.

Default: The first value found for each job attribute, using this order:

1. The value in a corresponding JCL parameter specified on the DD statement.
2. The value in a corresponding JCL parameter specified on the first OUTPUT statement referred to in the OUTPUT parameter on the DD statement.
3. The value in a corresponding JCL parameter specified on the first default OUTPUT statement in the job step.
4. The value in a corresponding JCL parameter specified on the first default OUTPUT statement in the job.
5. The value specified in the printer definition.
6. The JES default value for the corresponding JCL parameter. However, the JES default values for the CHARS, UCS, PAGEDDEF, or FCB parameters are not used to transform data.

Examples:

- This example shows how to submit output to the Print Interface subsystem named AOP1:

```
//DD1 DD SUBSYS=(AOP1,'myprinter')
```
- This example shows how to submit output to the subsystem named AOP1 and specify that the output from the transform should include only pages 1 through 10 and should be printed on both sides of the sheet. The PCL to AFP, PostScript to AFP, and PDF to AFP transforms support the **-p** option.

```
//DD1 DD SUBSYS=(AOP1,'myafpprinter',  
//      'filter-options="-p 1-10" duplex=yes')
```
- This example shows how to submit output to the subsystem named AOP1 and specify attributes in an HFS file named /u/myuserid/myattributes:

```
//DD1 DD SUBSYS=(AOP1,'myprinter','attributes=/u/myuserid/myattributes')
```

Parameters of the DD JCL statement that the Print Interface subsystem supports

Table 8 summarizes the parameters on the DD JCL statement, other than the SUBSYS parameter, that the Print Interface subsystem supports. It also describes the special considerations that apply when you use the Print Interface subsystem.

Table 8. Parameters of the DD JCL statement that the Print Interface subsystem supports

DD statement parameter	Print Interface subsystem considerations
BURST CHARS COPIES FLASH UCS	If you do not specify one of these parameters, the corresponding value in the printer definition is used. If none is specified, the standard default value is used. However, JES default values for the CHARS and UCS parameters are not used to transform data.
COPIES	<p>If you do not specify one of these parameters, the corresponding value in the printer definition is used. If none is specified, the default is one copy.</p> <p>The administrator can limit the number of copies that you can print. If you exceed the allowed limit, the Print Interface subsystem does not print any data sets in the job step.</p> <p>If you specify COPIES on both the DD and the OUTPUT JCL statement, COPIES on the DD statement is used.</p>

Table 8. Parameters of the DD JCL statement that the Print Interface subsystem supports (continued)

DD statement parameter	Print Interface subsystem considerations
DCB	Specify values in the DCB parameter that are suitable for data that your application writes to this DD statement. If you do not specify either the DCB OPTCD=J subparameter or the TRC parameter on the OUTPUT JCL statement, the TRC value in the printer definition is used.
DSNAME	Begin the name with two ampersands (&&). Follow the ampersands with 1 to 8 alphanumeric or national (\$, #, @) characters, a hyphen, or a character X'CO'. The first character after the ampersands must be alphabetic or national (\$, #, @). If you specify another format, you receive a JCL error.
LRECL	Specify values in this parameter that are suitable for data that the application writes to this DD statement.
OUTPUT	Refer to only one OUTPUT JCL statement. The Print Interface subsystem ignores all references except for the first one.
SEGMENT SYSOUT	Not allowed. If you specify one of these parameters with the SUBSYS parameter, you receive a JCL error.
All other DD parameters	The Print Interface subsystem does not use any other DD parameters. However, JES might use them.

Parameters of the OUTPUT JCL statement that the Print Interface subsystem supports

Table 9 summarizes the parameters of the OUTPUT JCL statement that the Print Interface subsystem supports. It also describes some special considerations that apply when you use the Print Interface subsystem.

Table 9. Parameters of the OUTPUT JCL statement that the Print Interface subsystem supports

OUTPUT statement parameter	Print Interface subsystem considerations
CLASS DEST FORMS	IP PrintWay does not use these values to select a printer definition. The Print Interface subsystem and IP PrintWay use only the printer definition specified in the SUBSYS parameter or, if none is specified, the printer definition in the FSSDATA parameter. If you do not specify one of these parameters, the corresponding value in the printer definition is used. If none is specified, the standard JES default is used. The administrator can limit the values you can specify in the FORMS parameter. If you specify a value that is not allowed, you receive a JCL error.
COPIES DATAACK DUPLEX	If you do not specify one of these parameters, the corresponding value in the printer definition is used. If none is specified, the standard JES default is used. The administrator can limit the values you can specify in these parameters. If you specify a value that is not allowed, you receive a JCL error.

Table 9. Parameters of the OUTPUT JCL statement that the Print Interface subsystem supports (continued)

OUTPUT statement parameter	Print Interface subsystem considerations
DEFAULT	The Print Interface subsystem uses only <i>one</i> OUTPUT JCL statement, in this order: <ol style="list-style-type: none"> 1. The first OUTPUT JCL statement referred to in the OUTPUT parameter on the DD statement 2. The first OUTPUT JCL statement with DEFAULT=YES in the same job step 3. The first OUTPUT JCL statement with DEFAULT=YES in the job
GROUPID	The Print Interface subsystem uses the specified group ID. However, JES always places the output data set that Print Interface allocates on the JES spool in a separate JES output subgroup regardless of the value specified in this parameter.
JESDS	Ignored
All other OUTPUT parameters	If you do not specify a parameter on the OUTPUT statement, the corresponding value specified in the printer definition is used. If none is specified, the standard JES default is used. However, the JES default values for the PAGEDEF and FCB parameters are not used to transform data. Parameters defined after March 1, 2002 are not supported unless support was added in an Infoprint Server PTF.

JCL statements that the Print Interface subsystem does not support

The Print Interface subsystem does not support these JCL statements:

- The JES2 /*OUTPUT JCL statement is ignored.
- The JES3 /*FORMAT JCL statement is ignored.

JCL parameters for distribution information

Figure 13 summarizes the parameters you can specify on an OUTPUT JCL statement to help identify and distribute output:

OUTPUT JCL Statement:

```
ADDRESS=('address text'[,...])
BUILDING='building text'
DEPT='department text'
NAME='name text'
ROOM='room text'
TITLE='description of output'
```

Figure 13. Summary of JCL parameters for the distribution of output

The values you specify in these parameters can be printed on a separator sheet if your installation writes an IP PrintWay exit that creates a separator sheet. IP PrintWay can also pass the value specified in the TITLE parameter to a remote printer. Depending on how the printer definition and the printer are configured, this title can print on the separator page (banner page) generated by the printer's LPD.

AFP parameters for remote printing with Infoprint Manager or Infoprint Server

This section lists the JCL parameters that you can specify on an OUTPUT or DD statement for IP PrintWay to send to either Infoprint Manager or Infoprint Server running on a remote system. IP PrintWay sends these parameters to the target system only if the administrator selects the **Remote PSF** option in the printer definition in the Printer Inventory.

These JCL parameters specify AFP options that Infoprint Manager and PSF for OS/390 use when you print on an IBM AFP printer. Also, data transforms provided with Infoprint Manager, Infoprint Server Transforms, and other transform products can use some of these parameters when transforming AFP and line data to another format, such as PCL or PostScript.

IP PrintWay sends the values for these JCL parameters to the target system:

ADDRESS	DEPT	INTRAY	OUTBIN
BUILDING	DEST	NAME	PAGEDEF
CHARS	DUPLEX	OFFSETXB	PRMODE ¹
CLASS	FCB	OFFSETXF	ROOM
COPIES	FORMDEF	OFFSETYB	TITLE
DATAACK	FORMS	OFFSETYF	TRC
			UCS

1. Values other than SOSI1, SOSI2, and SOSI3 are ignored.

For information about how IP PrintWay sends these and other JCL values to Infoprint Manager, see *z/OS Infoprint Server Operation and Administration*.

JCL examples

In the examples, assume that:

- Class P is a JES work-selection criterion for the IP PrintWay output writer (FSA).
- Class P and destination DEPT001 are printer-selection values specified in a printer definition.
- pc11 is a printer definition that does not specify a form name.
- PS1 is a destination name.
- Class P, destination DEPT002, and form name WIDE are printer-selection values specified in another printer definition.
- myoptions is the name of a set of components in the Printer Inventory.
- afpprinter is the printer definition for a printer attached to a remote system running Infoprint Manager or Infoprint Server.

The examples are all JES2 examples. For differences between JES2 and JES3, see *z/OS MVS JCL Reference*.

Direct output to IP PrintWay and to a printer by specifying the printer definition name

These examples show how to direct an output data set to IP PrintWay and to a printer by specifying the printer definition name.

Because these examples do not specify retry values, retention periods, or the name of an options component, IP PrintWay uses the values defined by your administrator

in this printer definition. If these values are not defined in the printer definition, IP PrintWay uses the standard defaults described in “JCL parameters” on page 118.

1. In this example, the OUTPUT statement specifies the printer definition name myprinter.

```
//PWAYJOB1 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,FSSDATA='printer=myprinter'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

2. In this example, the OUTPUT statement specifies the printer definition name myprinter and IP address 99.123.453. IP PrintWay uses this IP address instead of the address defined in myprinter. It uses the rest of the information in the myprinter printer definition.

```
//PWAYJOB2 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,FSSDATA='printer=myprinter',DEST='IP:99.153.123.232'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

Direct output to IP PrintWay and to a printer by specifying a host name or an IP address

These examples show how to direct an output data set to IP PrintWay and to a printer by specifying the host name or IP address of the target system and the name of the print queue.

Because these examples do not specify retry values, retention periods, or the name of an options component, IP PrintWay uses default values defined by your installation in a default printer definition. If no default printer definition exists, IP PrintWay uses the standard defaults described in “JCL parameters” on page 118.

1. In this example, the OUTPUT statement specifies the printer’s host name BOULDER.XYZ.COM and print queue lpd1.

```
//PWAYJOB3 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,DEST='IP:BOULDER.XYZ.COM',PRTQUEUE='lpd1'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

2. In this example, the OUTPUT statement specifies the IP address (99.123.453) and the name of the print queue (lpd1).

```
//PWAYJOB4 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,DEST='IP:99.153.123.232',PRTQUEUE='lpd1'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

Direct output to IP PrintWay and to a printer by specifying DEST, CLASS, or FORMS

These examples show how to specify the destination, class, or form name to direct an output data set to a printer controlled by IP PrintWay. IP PrintWay uses a printer whose printer definition values matches the values you specify in the JCL.

You can override the name of the print queue in the printer definition, as shown in Example 3 on page 146.

1. In this example, the DD statement specifies a destination name, class, and form name. The destination name and class match values in a printer definition. The DD statement also specifies a form name, but the printer definition does not specify one. Therefore, IP PrintWay does not use the form name as a printer selection criterion.

```
//PWAYJOB5 JOB ...
//STEP1 EXEC PGM=USERA
//DD1 DD SYSOUT=(P,,WIDE),DEST=DEPT001
```

Note: If the form name is more than 4 characters, you must specify the name on the OUTPUT statement, as shown in Example 3.

2. In this example, the OUTPUT statement specifies destination name and class. It does not specify a form name. A JES default is used for the form name.

```
//PWAYJOB6 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,DEST=DEPT001
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

3. In this example, the OUTPUT statement specifies the destination name, class, and form name. The print queue name, lpd2, overrides the name of the print queue specified in the printer definition.

```
//PWAYJOB7 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,FORMS=WIDE,DEST=DEPT002,PRTQUEUE='lpd2'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

Direct output to IP PrintWay and to more than one printer or e-mail destination

These examples show how to direct a data set to IP PrintWay and to send it to more than one printer or e-mail destination at the same time by specifying multiple OUTPUT statements. The OUTPUT parameter on the DD statement refers to two OUTPUT JCL statements. Therefore, JES creates two output data sets.

1. In this example, the OUTPUT statements specify two different destination names:

```
//PWAYJOB8 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT CLASS=P,DEST=DEPT001
//OUTDS2 OUTPUT CLASS=P,DEST=DEPT002
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS1,*.OUTDS2)
```

2. In this example, the OUTPUT statements specify the IP addresses of two printers:

```
//PWAYJOB9 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT DEST='IP:99.153.123.232',PRTQUEUE='lpd1'
//OUTDS2 OUTPUT DEST='IP:99.153.123.232',PRTQUEUE='lpd2'
//DD1 DD SYSOUT=P,OUTPUT=(*.OUTDS1,*.OUTDS2)
```

Specify components in the Printer Inventory

These examples show how to specify the name of Printer Inventory components defined by your administrator and used by IP PrintWay.

1. In this example, the OUTPUT statement specifies the name of a printer definition and the name of components in the Printer Inventory that contain IP PrintWay options. IP PrintWay uses components named myoptions instead of the options in the printer definition.

```
//PWAYJOBA JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT FSSDATA='printer=myprinter',PRTOPTNS='myoptions'
//DD1 DD SYSOUT=P,OUTPUT=(*.OUTDS)
```

2. In this example, the OUTPUT statement specifies the name of the print queue and the IP address of the host. IP PrintWay uses components named myoptions instead of the options in the default printer definition.

```
//PWAYJOB JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,DEST='IP:99.153.123.232',PRTQUEUE='lpd1',
// PRTOPTNS='myoptions'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

Specify retry values

These examples show how to specify these IP PrintWay retry values:

- Retry time of 1 minute. IP PrintWay retries a failed transmission one time immediately, then waits 8 minutes between retries.
- Retry limit of 3 times. If the immediate retry fails, IP PrintWay retries a maximum of 3 more times.

1. In this example, the OUTPUT statement specifies a printer definition name. IP PrintWay uses the retry values specified on the OUTPUT statement instead of the values in this printer definition.

```
//PWAYJOB JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT FSSDATA='printer=myprinter',
// RETRYL=3,RETRYT='0000:09:00'
//DD1 DD SYSOUT=P,OUTPUT=(*.OUTDS)
```

2. In this example, the OUTPUT statement specifies the name of the print queue and the IP address of the host. IP PrintWay uses the retry values specified on the OUTPUT statement instead of the values in the default printer definition.

```
//PWAYJOB JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,DEST='IP:99.153.123.232',PRTQUEUE='lpd1',
// RETRYL=3,RETRYT='0000:09:00'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

Specify retention periods

These examples show how to specify these IP PrintWay retention periods:

- Retention period of 1 day (24 hours) if the transmission is successful
 - Retention period of 4 days (96 hours) if the transmission fails
1. In this example, the OUTPUT statement specifies a printer definition name. IP PrintWay uses the retention values specified on the OUTPUT statement instead of the values in this printer definition.

```
//PWAYJOB JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT FSSDATA='printer=myprinter',
// RETAINF='96:00:00',RETAINS='24:00:00'
//DD1 DD SYSOUT=P,OUTPUT=(*.OUTDS)
```

2. In this example, the OUTPUT statement specifies a form and destination name. IP PrintWay uses the retention values specified on the OUTPUT statement instead of the values in the printer definition for the printer that matches this form and destination name.

```
//PWAYJOB JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,FORMS=WIDE,DEST=DEPT001,
// RETAINF='96:00:00',RETAINS='24:00:00'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

3. In this example, the OUTPUT statement specifies the name of the print queue and the IP address of the host. IP PrintWay uses the retention values specified on the OUTPUT statement instead of the values in the default printer definition.


```
//PWAYJOBG JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,DEST='IP:99.153.123.232',PRTQUEUE='lpd1',
// RETAINF='96:00:00',RETAINS='24:00:00'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

Specify AFP resources for printing on a remote PSF system

This example shows how to specify a page definition and coded font for printing on an AFP printer attached to a system that is running either Infoprint Manager or Infoprint Server with PSF for OS/390. IP PrintWay prefixes P1 to the specified page definition name before transmitting the value.

```
//PWAYJOBH JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,FSSDATA='printer=afpprinter',
// CHARS=60DB,PAGEDEF=000001
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS)
```

Note: The administrator must select the **Remote PSF** option in the printer definition in the Infoprint Server Printer Inventory.

Send line data to an e-mail destination as text data

This example shows how to send two output data sets that contain line data to an e-mail destination in text format. This example specifies the subject of the e-mail in the TITLE parameter, and the names of the attachments in the DSNAME parameters.

This example assumes that the administrator has set up the printer definition in the Printer Inventory:

- The IP PrintWay printer definition is named deptmail.
- The e-mail protocol is selected, and the recipient e-mail address list or a z/OS UNIX sendmail alias name is specified.
- No transform is specified for line data and the **Resubmit for filtering** option is not selected. Therefore, the default is that IP PrintWay converts line data in the data set to text format.
- The **Concatenate job** option is selected in the **Dataset grouping** field. In a JES2 environment, this option causes IP PrintWay to send output data sets that are in the same JES output subgroup in the same e-mail.

```
//PWAYJOBI JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,TITLE='Monthly Report',
// FSSDATA='printer=deptmail'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS),DSNAME=&&SALES
//DD2 DD SYSOUT=(,),OUTPUT=(*.OUTDS),DSNAME=&&INVENTORY
```

Results: The recipients listed in the printer definition receive an e-mail:

- The sender of the e-mail is the user ID who ran the job. For example, USER1@DOMAIN1.
- The subject of the e-mail is Monthly Report.
- In a JES2 environment, the e-mail has two attachments: SALES.txt and INVENTORY.txt. Both attachments are in text format and can be viewed with any text editor.
- In a JES3 environment, two e-mails are sent. One e-mail contains attachment SALES.txt. The other e-mail contains attachment INVENTORY.txt. Both attachments are in text format and can be viewed with any text editor.

Send line or AFP data to an e-mail destination as PDF data and print the AFP data on an AFP printer

This example shows how to (1) send an output data set with either line or AFP data to one or more e-mail addresses as an attachment in PDF format and (2) print it on an IBM AFP printer controlled by PSF for OS/390. This example specifies the subject of the e-mail in the TITLE parameter and the name of the attachment in the DSNNAME parameter.

This example assumes that the administrator has set up a printer definition for the e-mail destination in the Printer Inventory:

- The IP PrintWay printer definition is named deptmail.
- The e-mail protocol is selected and the recipient e-mail address list or a z/OS UNIX sendmail alias name is specified in the printer definition.
- The AFP to PDF transform is specified for the line data and MO:DCA-P data formats, and the **Resubmit for filtering** option is selected.
- AFP resource libraries are specified either in the printer definition or in the transform configuration file, **aopxfd.conf**. If not, you must specify the USERLIB JCL parameter on the OUTDS1 OUTPUT statement.

This example also assumes that the system programmer has defined the PSF-controlled printer to JES so that JES directs data sets with CLASS F and DEST PRT633 to the PSF-controlled printer.

```
//PWAYJOB JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT CLASS=P,FORMDEF=MYDEF,TITLE='Monthly Report',
// FSSDATA='printer=deptmail'
//OUTDS2 OUTPUT CLASS=F,FORMDEF=MYDEF,TITLE='Monthly Report',
// DEST=PRT633'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS1,*.OUTDS2),DSNAME=&&REPORT
```

Results:

- The recipients listed in the printer definition deptmail receive an e-mail:
 - The sender of the e-mail is the user ID who ran the job. For example, USER1@DOMAIN1.
 - The subject of the e-mail is Monthly Report.
 - The e-mail attachment is named REPORT.pdf and is in PDF format. The attachment can be viewed with a PDF viewer such as Adobe Acrobat Reader.
- The file is printed on the PSF-controlled printer defined with JES work-selection criteria of CLASS F and DEST PRT633.

Send line or AFP data to an e-mail destination as AFP data

This example shows how to send an output data set that contains either AFP data or line data with AFP resources to an e-mail destination as an AFP file. This example specifies the subject of the e-mail in the TITLE parameter and the name of the attachment in the DSNNAME parameter.

This example uses the IBM ACIF program to collect AFP resources into a separate file and concatenate that file to the line or AFP data file so that the e-mail recipient can view the file using the IBM AFP Viewer plug-in for Windows and also print the file.

This example assumes that the administrator has set up the printer definition in the Printer Inventory:

- The IP PrintWay printer definition is named deptmail.
- The e-mail protocol is selected and the recipient e-mail address list or a z/OS UNIX sendmail alias name is specified in the printer definition.
- No transform is specified for the AFP data format, and the IP PrintWay formatting option **none** is selected.

```
//PWAYJOBK JOB ...
//ACIF      EXEC  PGM=APKACIF,PARM='PARMDD=PARMS'
//SYSPRINT DD   SYSOUT=*
//INPUT     DD   DSNAME=MYFILE.AFP,DISP=SHR
//OUTPUT    DD   DUMMY
//RESOBJ     DD   DSNAME=&&RESLIB,DISP=(,PASS),
//           SPACE=(CYL,(5,5),RLSE),
//           UNIT=3390,VOL=SER=USR003,
//           DCB=(LRECL=12284,BLKSIZE=12288,RECFM=VBM)
//PARMS      DD   *
INDEXOBJ = NONE           /* Do not create INDEX output */
RESTYPE  = ALL            /* Collect all resource types */
CCTYPE   = M              /* Carriage control type */
MCF2REF  = CF             /* Collect coded fonts */
FONTLIB  = SYS1.FONT300, /* Font libraries */
          SYS1.FONTOLN
USERLIB  = MY.USERLIB     /* Other user resources */
FDEFLIB  = SYS1.FDEFLIB  /* Form definition library */
FORMDEF  = F1MYFDEF       /* Form definition to use */
/*
//IEBGENER EXEC  PGM=IEBGENER,COND=(0,NE)
//SYSPRINT DD   SYSOUT=*
//SYSIN     DD   DUMMY
//OUTDS      OUTPUT CLASS=P,TITLE='Monthly Report',
//           FSSDATA='printer=deptmail'
//SYSUT1     DD   DSNAME=*.ACIF.RESOBJ,DISP=(OLD,DELETE)
//           DD   DSNAME=MYFILE.AFP,DISP=SHR
//SYSUT2     DD   SYSOUT=(,),OUTPUT=(*.OUTDS),DSNAME=&&REPORT
```

Results: The recipients listed in the printer definition deptmail receive an e-mail:

- The sender of the e-mail is the user ID who submitted the job. For example, USER1@DOMAIN1
- The subject of the e-mail is Monthly Report.
- The e-mail attachment is named REPORT.afp and is in AFP format with all AFP resources inline. The attachment can be viewed with the IBM AFP Viewer plug-in for Windows.

Print line or AFP data on a PostScript or PCL printer using the resubmit for filtering function

These examples show how to print line data and AFP data to a PostScript or PCL printer. These examples assume that your administrator has configured the printer definition in the Printer Inventory to use the AFP to PostScript or AFP to PCL transform and also selected the **Resubmit for filtering** option. Because the AFP to PCL, AFP to PDF, and AFP to PostScript transforms use the same JCL parameters as PSF for OS/390 uses, you can specify the same JCL parameters as you do when you print on an AFP printer.

1. In this example, AFP output is sent to a PostScript printer. Because this example does not specify a form name, a JES default is used for the form name. The last qualifier of the fully qualified data set name on the JES spool will be MYFILE. Because the **Resubmit for filtering** option is selected in the printer definition, Infoprint Server dynamically allocates a second output data set on the JES spool during processing. The last qualifier of this data set's fully qualified name will also be MYFILE.

```

//TRJOB1 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS OUTPUT CLASS=P,DEST=PS1
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS),DSNAME=&&MYFILE

```

2. In this example, an AFP job is sent to a PCL printer. It is printed with a user defined form definition F1MYDEF which is in the user library MYLIB.

```

//TRJOB2 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT CLASS=P,FORMDEF=MYDEF,USERLIB=MYLIB,FSSDATA='printer=pcl1'
//DD1 DD SYSOUT=(,),OUTPUT=(*.OUTDS1),DSNAME=&&MYFILE

```

Print line or AFP data on a PostScript printer using the Print Interface subsystem

These examples show how to print line data and AFP data on a PostScript printer. These examples assume that your administrator has created two IP PrintWay printer definitions named mypsprinter and anypsprinter in the Infoprint Server Printer Inventory:

- The AFP to PostScript transform is specified in both printer definitions.
- Class P, the JES work-selection criterion for IP PrintWay, is specified in both printer definitions. Therefore, CLASS=P is not specified on the OUTPUT JCL statement in these examples.
- Printer definition mypsprinter contains the printer's IP address and print queue name.
- Printer definition anypsprinter specifies the LPR transmission protocol, but does *not* specify your printer's IP address and print queue name. Example 3 shows how to specify your printer's IP address and print queue name on the OUTPUT JCL statement.

1. In this example, the Print Interface subsystem named AOP1 transforms data in two data sets to PostScript format and writes the PostScript data to two output data sets on the JES spool. The last qualifiers of the data sets names are DATA1 and DATA2. The subsystem uses options specified in mypsprinter. IP PrintWay then prints both data sets on the printer whose address is specified in mypsprinter.

```

//SSJOB1 JOB ...
//STEP1 EXEC PGM=USERA
//DD1 DD SUBSYS=(AOP1,'mysprinter'),DSNAME=&&DATA1
//DD2 DD SUBSYS=(AOP1,'mysprinter'),DSNAME=&&DATA2

```

2. In this example, the Print Interface subsystem named AOP1 transforms data to PostScript format and writes the PostScript data to an output data set on the JES spool. The subsystem uses options specified in mypsprinter. However, it uses form definition F1MYDEF in library MYLIB to transform the data. IP PrintWay then prints the data on the printer whose address is specified in mypsprinter.

```

//SSJOB2 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT FORMDEF=MYDEF,USERLIB=MYLIB
//DD1 DD SUBSYS=(AOP1,'mysprinter'),OUTPUT=(*.OUTDS1)

```

3. In this example, the Print Interface subsystem transforms data to PostScript format and writes the PostScript data to an output data set on the JES spool. The subsystem uses options specified in anypsprinter. IP PrintWay then prints the data to queue myqueue on the printer with IP address 99.153.123.232.

```

//SSJOB3 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT DEST='IP:99.153.123.232',PRTQUEUE='myqueue'
//DD1 DD SUBSYS=(AOP1,'anysprinter'),OUTPUT=(*.OUTDS1)

```

Print PostScript, PCL, or PDF data on an IBM AFP printer using the Print Interface subsystem

These examples show how to print PostScript, PCL, and PDF data on an IBM AFP printer controlled by PSF for OS/390. These examples assume that your administrator has created two PSF for OS/390 printer definitions named `myafpprinter` and `anyafpprinter` in the Infoprint Server Printer Inventory:

- The PostScript to AFP, PCL to AFP, and PDF to AFP transforms are specified in both printer definitions. The **%filter-options** transform option is also specified to allow job submitters to specify transform options as shown in example 2.
- Printer definition `myafpprinter` specifies the class and destination name of the PSF-controlled printer. (CLASS and DEST are JES work-selection parameters that are typically used to direct output from the JES spool to a PSF-controlled printer.)
- Printer definition `anyafpprinter` does *not* specify the CLASS and DEST values for your PSF-controlled printer. Example 3 shows how to specify your printer's CLASS and DEST work-selection values on the OUTPUT JCL statement.

1. In this example, the Print Interface subsystem named `A0P1` transforms data to AFP format and writes the AFP data to output data sets on the JES spool. The last qualifiers of the data sets names are `DATA1` and `DATA2`. The subsystem uses options specified in printer definition `myafpprinter`. PSF for OS/390 then prints the data sets on the AFP printer whose CLASS and DEST values match those specified in `myafpprinter`.

```
//SSJOB4 JOB ...
//STEP1 EXEC PGM=USERA
//DD1 DD SUBSYS=(A0P1,'myafpprinter'),DSNAME=&&DATA1
//DD2 DD SUBSYS=(A0P1,'myafpprinter'),DSNAME=&&DATA2
```

2. In this example, the Print Interface subsystem transforms data to AFP format and writes the AFP data to an output data set on the JES spool. The subsystem uses options specified in printer definition `myafpprinter`. Because the **filter-options** attribute is specified in the SUBSYS parameter, it writes only the first 10 pages of the transformed data to the output data set. PSF for OS/390 then prints the data set on the AFP printer whose CLASS and DEST values match those specified in `myafpprinter`. PSF for OS/390 uses form definition `F1MYDEF`, which is in library `MYLIB`, to format the AFP data.

```
//SSJOB5 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT FORMDEF=MYDEF,USERLIB=MYLIB
//DD1 DD SUBSYS=(A0P1,'myafpprinter',
//      'filter-options="-p 1-10"'),
//      OUTPUT=(*.OUTDS1)
```

3. In this example, the Print Interface subsystem named `A0P1` transforms data to AFP format and writes the AFP data to an output data set on the JES spool. The subsystem uses options specified in printer definition `anyafpprinter`. The subsystem allocates the output data set with `CLASS=F` and `DEST=PRT003`. PSF for OS/390 then prints the data set on the AFP printer that processes data sets with `CLASS=F` and `DEST=PRT003`.

```
//SSJOB6 JOB ...
//STEP1 EXEC PGM=USERA
//OUTDS1 OUTPUT CLASS=F,DEST=PRT003
//DD1 DD SUBSYS=(A0P1,'anyafpprinter'),OUTPUT=(*.OUTDS1)
```

Chapter 5. Printing using the AOPPRINT JCL procedure

The AOPPRINT Job Control Language procedure, provided in SYS1.PROCLIB, lets you submit print requests from z/OS. This procedure lets you take advantage of all the features of Infoprint Server:

- You can specify job attributes.
- If Infoprint Server Transforms or another optional transform product is installed, you can automatically transform jobs from one data format to another.
- Infoprint Server validates that data can print on the selected printer.

Tips:

1. Your administrator can customize the AOPPRINT procedure. For information, see *z/OS Infoprint Server Customization*.
2. For information about the JOB, EXEC, DD, and IF/THEN/ELSE/ENDIF JCL statements (which appear in the examples in this chapter), see *z/OS MVS JCL Reference*.

Sending a file to an e-mail destination

With the AOPPRINT procedure, you can send the file to an e-mail destination instead of to a printer. When you send a file to an e-mail destination, your administrator can specify the e-mail address list of the recipients in the printer definition for the e-mail destination in the Printer Inventory, or you can specify the address list in an alias file that your administrator defines to z/OS UNIX sendmail. For information, see “Specifying the e-mail address list in an alias file” on page 112.

The e-mail has these characteristics:

- The file is an e-mail attachment. The name of the attachment is the name specified in the **sysout-dataset-name** job attribute. If this attribute is not specified, the attachment name is DD#SYSIN.
The attachment name contains an extension that indicates the type of data in the file. For example, txt indicates text format and pdf indicates PDF format.
- The subject of the e-mail is the value specified in the **title-text** job attribute or the default title your administrator specified in the Allocation section of the printer definition. If none is specified, the user ID of the user who ran the job is used.
- The sender is the user ID of the user who ran the job at the domain name of the z/OS system.
- You can receive replies from the e-mail unless a firewall prevents the z/OS system from receiving replies from the sending system. To receive replies, use the z/OS UNIX **mail** or **mailx** command. To use these commands, your ID must be a valid z/OS UNIX user ID.

AOPPRINT parameters

```
ERRCLASS=class
OPTIONS='attribute=value'...
OUTCLASS=class
PRINTER=printer_definition_name
```

Figure 14. AOPPRINT JCL parameters: format

ERRCLASS=class

Specifies the 1 character alphanumeric name of the system output data set (sysout) class for error messages. The name of the data set where error messages are written is specified by the STDERR data definition name (DDname).

Default: Infoprint Server uses the class specified by your administrator.

OPTIONS='attribute=value ...'

Specifies job attributes and values to use in processing the job. For descriptions of all job attributes, see “Attribute listing” on page 87. Enter the attribute names in lowercase. Separate attributes with a space.

Using an attributes file: You can store attributes and values in a UNIX file (such as an HFS file) or in an MVS data set. Use the attribute called `attributes` to specify the file or DD name from which attributes are to be read, as in this example:

```
OPTIONS='attributes=bigjob.att'
```

If the attributes are stored in an MVS data set, you must specify four single quotation marks before the data set name and four single quotation marks after it.

For how to create an attributes file, see “Creating an attributes file” on page 86.

OUTCLASS=class

Specifies the 1 character alphanumeric name of the sysout class for informational messages. The name of the data set where informational messages are written is specified by the STDOUT DDname.

Default: Infoprint Server uses the class specified by your administrator.

PRINTER=printer_definition_name

Specifies the name of a printer definition created by your administrator. The printer definition identifies a printer or an e-mail destination and sets default values for transform options and for some job attributes. The name of the printer definition is case-sensitive. Enter it exactly as your administrator tells you.

Default: Infoprint Server uses the default printer definition specified by your administrator.

AOPPRINT DD statements

The AOPPRINT JCL procedure lets you specify these DD statements (notice that you cannot specify an OUTPUT statement—if you specify one, it is ignored):

STDERR

Specifies the system output data set where error messages are to be written. The ERRCLASS parameter defines the class of this data set.

STDOUT

Specifies the system output data set where informational messages are to be written. The OUTCLASS parameter defines the class of this data set.

SYSIN

Specifies the data set to be printed. You can concatenate data sets that have the same data format; for example, line data or AFP data. However, you *cannot* concatenate data sets that contain PDF data.

AOPPRINT results

After Infoprint Server accepts the print job, AOPPRINT returns an Infoprint Server job ID, which you can use to query and cancel the job. The Infoprint Server job ID is returned in a message in the STDOUT data set. For example:

```
AOP007I Job 14584 successfully spooled to myprinter.
```

The Infoprint Server job ID can help the system operator find your job on the JES spool. The job ID field of the data set that Infoprint Server allocates on the JES spool contains the same Infoprint Server job ID. The Infoprint Server job ID is different, however, from the z/OS job ID, which is a unique job ID that z/OS assigns to the data set. JES operator commands return the z/OS job ID.

AOPPRINT examples

These examples show how to use the AOPPRINT JCL procedure:

Print a file on the default printer

This example shows how to submit the data set FILE1.LISTPS to your default printer:

```
//JOB1 JOB 707,JONES
//PRINT EXEC AOPPRINT
//SYSIN DD DSNAME=FILE1.LISTPS,DISP=SHR
```

Print a file on a specified printer

This example shows how to submit the data set FILE1.LISTPS to the printer fred:

```
//JOB2 JOB D31,'H. EVANS'
//PRINTPS EXEC AOPPRINT,PRINTER='fred'
//SYSIN DD DSNAME=FILE1.LISTPS,DISP=SHR
```

Print multiple copies of a data set

This example shows how to submit a data set to the default printer and specify two copies of the job:

```
//JOB3 JOB , 'MARTHA'
//PRINT2 EXEC AOPPRINT,OPTIONS='copies=2'
//SYSIN DD DSNAME=MYJOB.PDF,DISP=SHR
```

Tip: VTAM-controlled printers and some IPP-enabled printers do not support printing more than one copy. In this case, only one copy prints.

Submit and hold a job

This example shows how to submit the data set FILE1.LISTPS to Printer1 and to hold it so that it does not print until the operator releases it:

```
//JOB5 JOB (DIV1,GROUP7),OPERATOR
//PRHOLD EXEC AOPPRINT,PRINTER='Printer1',OPTIONS='hold=true'
//SYSIN DD DSNAME=FILE1.LISTPS,DISP=SHR
```

Specify a code page for ASCII jobs

This example shows how to print the data sets JAN.REPORT and FEB.REPORT on the default printer and to specify the code page ISO8859-1:

```
//JOB6 JOB (DIV1,GROUP7), 'ANNE BROWN'
//PRINT EXEC AOPPRINT,OPTIONS='document-codepage=ISO8859-1'
//SYSIN DD DSNAME=JAN.REPORT,DISP=SHR
// DD DSNAME=FEB.REPORT,DISP=SHR
```


Print with error processing

This example shows how to print the data set BIGJOB.PCL on Printer1, writing error messages to the data set BIGJOB.PCL. This example calls one program if the job succeeds, or a different program if it fails.

```
//JOB8      JOB   , 'MARTHA'
//PRINTERR  EXEC  AOPPRINT, PRINTER='Printer1'
//SYSIN     DD    DSNAME=BIGJOB.PCL, DISP=SHR
//STDERR    DD    DSNAME=BIGJOB.ERR
//*
//          IF    PRINT.LP.RC  = 0 THEN
//FAIL      EXEC  PGM=BADJOB
//          ELSE
//SUCCEED    EXEC  PGM=GOODJOB
//          ENDIF
```

Print in-stream data

This example shows how to print data from the JCL input stream:

```
//JOB9      JOB   D10, CHARLIE
//HELLO     EXEC  AOPPRINT
//SYSIN     DD    *
              Hello, world!
/*
```

Send a file to an e-mail destination

This example shows how to send data set FILE1.AFP to the e-mail address list specified in printer definition deptmail, and specify a subject for the e-mail, a name for the e-mail attachment, and a form definition to be used when the AFP file is transformed to PDF format:

```
//JOBA      JOB   D31, 'H. EVANS'
//EMAIL     EXEC  AOPPRINT, PRINTER='deptmail',
//          OPTIONS='attributes=//DD:MYATTR'
//SYSIN     DD    DSNAME=FILE1.AFP, DISP=SHR
//MYATTR    DD    *
sysout-dataset-name=Report
title-text="Monthly Report"
form-definition=F1MYDEF
/*
```

Rules: In this example, the EXEC statement continues on a second line because a single line would be longer than 71 characters. When you continue a JCL statement, observe these rules:

1. Break after a complete parameter or subparameter, at or before column 71. A comma belongs with the preceding parameter or subparameter.
2. Code // in columns 1 and 2 of the continuation line.
3. Leave column 3 of the continuation line blank.
4. Continue the interrupted parameter or field starting in any column from 4 through 16.

This example assumes that the AFP to PDF transform is specified in printer definition deptmail and that AFP resources libraries are specified either in the printer definition or in the transform configuration file, **aopxfd.conf**. If the AFP resource libraries are not specified elsewhere, specify the libraries in the **resource-library** job attribute.

Results: The recipients listed in printer definition deptmail receive an e-mail:

- The sender of the e-mail is the user ID of the user who ran the AOPPRINT procedure.
- The subject of the e-mail is Monthly Report.
- File FILE1.AFP is attached to the e-mail. The name of the attachment is: REPORT. The file is in PDF format and can be viewed and printed with a PDF viewer such as Adobe Acrobat Reader.

AOPPRINT exit values

- 0** Infoprint Server accepted the request.
- >0** An error occurred.

Chapter 6. Transforming data with the AOPBATCH program

The AOPBATCH program (which Infoprint Server provides in SYS1.LINKLIB) lets you submit a batch job to transform data to and from the Advanced Function Presentation data format, using transforms provided by the Infoprint Server Transforms product (5697-F51) or another optional transform product, such as Infoprint XML Extender for z/OS (5655-J66).

AOPBATCH parameters

The AOPBATCH parameters are the name of the transform command, followed by transform options and arguments, in this format:

```
EXEC PGM=AOPBATCH,PARM='/transform_name transform_options'
```

/ The optional slash indicates that the PARM data that follows is input to AOPBATCH. If you omit the initial slash, your PARM data might be interpreted as C++ run-time options. You *must* include the initial slash if any of the PARM data itself includes a slash. For example, if the transform name is /mylib/ps2afp, specify: PARM='/mylib/ps2afp ...'.

transform_name

The name of an executable transform program that resides in an HFS file. The name of the transform program is case-sensitive. You can specify one of these Infoprint Server Transforms command names: **afp2pcl**, **afp2pdf**, **afp2ps**, **pcl2afp**, **pdf2afp**, **ps2afp**, and **sap2afp**. If you have XML Extender, you can also use **xml2afp**.

If the transform program does not reside in one of the directories specified in the PATH environment variable, also specify the pathname. You can use the STDENV DD statement to set the PATH environment variable if the default value set by AOPBATCH is not suitable. For information about the defaults set for environment variables, see “AOPBATCH DD statements” on page 160.

transform_options

Options and arguments accepted by transform. For a description of the transform command options and arguments, see the transform description in Chapter 2, “Printing from z/OS UNIX System Services using Infoprint Server commands” on page 23.

You must specify the transform input data set or file as a transform argument, and you must specify the **-o** transform option to identify where you want the transform to write its output. (This is because the transform cannot write its output to standard output and cannot read input from standard input.) To identify the transform input and output data set or file, you can specify either a DD statement name or a data set or file name. You must specify a DD statement name if you want to write the transform output to an MVS data set that does not already exist.

Specify the names of DD statements to the transform in this format:

```
//DD:DDname
```

The name of the DD statement is *DDname*.

When you specify an MVS data set name in the **-o** options, code two slashes before the data set name and enclose the data set name in two sets of single quotation marks if you specify a fully qualified data set name. If you do *not*

enclose the data set name in quotation marks, C/C++ assumes that the data set name is not fully qualified and adds a high-level qualifier to the name you specify:

- If you are running under TSO (batch or interactive), OS/390 C/C++ appends the TSO user prefix.
- If you are running under MVS batch or IMS (batch or online), OS/390 C/C++ appends the RACF user ID.
- If your system does not use RACF, C/C++ does not add a high-level qualifier.

For examples of different ways to specify transform input and output data sets and files, see “AOPBATCH examples” on page 161.

AOPBATCH DD statements

The AOPBATCH JCL procedure accepts these standard DD statements:

STDENV

Specifies environment variables for use by the transform. You can specify the environment variables in-stream in the JCL, in an MVS data set, or in a UNIX file. Specify the environment variables in the format *variable=value*, with one environment variable per line or record. Sequence numbers in columns 73 - 80 in data specified with the STDENV DD statement are ignored and *not* treated as part of the data.

If you omit the STDENV DD statement or do not specify one of the environment variables, AOPBATCH sets these default values, which are suitable for running Infoprint Server programs if your installation installed Infoprint Server files in the default directories:

- PATH=/usr/lpp/Printsrv/bin:/bin:/usr/bin
- LIBPATH=/usr/lpp/Printsrv/lib:/lib:/usr/lib
- NLSPATH=/usr/lpp/Printsrv/%L/%N:/usr/lib/nls/msg/%L/%N

AOPBATCH also sets the HOME environment variable to the user's home directory and sets the LOGIN variable to the user ID.

Note: Do *not* specify the _BPX_SHAREAS environment variable. AOPBATCH will set it appropriately.

STDERR

Specifies the system output data set where error messages are to be written. The data set can be an MVS data set or a UNIX file.

STDOUT

Specifies the system output data set where informational messages are to be written. The data set can be an MVS data set or a UNIX file.

You can also include DD statements to specify MVS data sets that contain input data to be transformed, the transformed output, or job attributes that are input to the transform. Do *not* use DD names STDIN, STDOUT, or STDERR to specify the transform input and output data sets. Instead, use other DD names, such as INPUT and OUTPUT, which are used in the examples.

Rules:

- If the output data set is an MVS data set, these requirements apply:
 - You must either allocate and catalog the data set before you run AOPBATCH, or include a DD statement in the AOPBATCH job to allocate the data set.

- The MVS output data set must be large enough to hold the output data stream. The size of the output data stream depends on the complexity of the document. If you run the **pcl2afp**, **pdf2afp**, or **ps2afp** transform, the type of image compression you select in the **-a** option also affects the size of the output data stream. Typically, an output AFP data stream is several times as large as the input data stream.
- If the output data set is to contain an AFP data stream, allocate a data set with these characteristics:
 - Record format: VBM
 - Record length: 8192 (8K) or larger
- If the output data set is to contain a PCL, PDF, or PostScript data stream, allocate a data set with these characteristics:
 - Record format: VB
 - Record length: 1024 or larger is recommended
- Specify a disposition of SHR or OLD if you want the transform to overwrite any existing data. Otherwise, specify a disposition of MOD to append the output to any existing data. If you do not specify any disposition, the transform overwrites any existing data.
- If you have not added the Language Environment run-time library (CEE.SCEERUN) or the C++ run-time library (CBC.SCLBDLL) to the system LNKLIST, specify these data sets in a STEPLIB DD statement.
- You can concatenate input data sets that have the same data format; for example, PostScript data or AFP data. However, you *cannot* concatenate data sets that contain PDF data.

AOPBATCH examples

These examples show how to use the AOPBATCH procedure to transform data.

Specify transform input and output in MVS data sets, and specify environment variables

This example shows how to transform data when the transform input is in an MVS data set and transform output is written to an MVS data set. Transform **ps2afp** reads PostScript input from data set HLQ.INPUT.PS and writes AFP output to data set HLQ.OUTPUT.AFP. HLQ represents the high-level qualifier; for example, your TSO or RACF user ID.

This example also shows how to specify environment variables in-stream in the STDENV DD statement. If you installed Infoprint Server and created Infoprint Server configuration files in default directories, you do *not* need to specify these environment variables and you can omit the STDENV DD statement.

```
//AOPBATCH JOB ...
//TRANSFORM EXEC PGM=AOPBATCH,PARM='/ps2afp -o //DD:OUTPUT //DD:INPUT'
//INPUT DD DSN=HLQ.INPUT.PS,DISP=SHR
//OUTPUT DD DSN=HLQ.OUTPUT.AFP,DISP=(NEW,CATLG,DELETE),
//          DCB=(RECFM=VBM,LRECL=32756,BLKSIZE=32760),
//          SPACE=(CYL,(1,1))
//STDOUT DD SYSOUT=*
//STDERR DD SYSOUT=*
//STDENV DD *
PATH=/usr/lpp/Printsrv/bin:/bin:/usr/bin
LIBPATH=/usr/lpp/Printsrv/lib:/lib:/usr/lib
NLSPATH=/usr/lpp/Printsrv/%L/%N:/usr/lib/nls/msg/%L/%N
AOPCONF=/etc/Printsrv/aopd.conf
/*
```

Specify transform input in a UNIX file and output in an MVS data set

This example shows how to transform data when the transform input is in a UNIX file and transform output is written to an MVS data set. The **pdf2afp** transform reads the PDF input from file **/tmp/input.pdf** and writes AFP output to **HLQ.OUTPUT.AFP**.

```
//AOPBATCH JOB ...
//TRANSFRM EXEC PGM=AOPBATCH,PARM='/pdf2afp -o //DD:OUTPUT /tmp/input.pdf'
//OUTPUT DD DSN=HLQ.OUTPUT.AFP,DISP=(NEW,CATLG,DELETE),
// DCB=(RECFM=VBM,LRECL=32756,BLKSIZE=32760),SPACE=(CYL,(1,1))
//STDOUT DD SYSOUT=*
//STDERR DD SYSOUT=*
```

Specify transform input in an MVS data set and output in a UNIX file

This example shows how to transform data when the transform input is in an MVS data set and transform output is written to a UNIX file. Transform **afp2pdf** reads the AFP input from data set **HLQ.INPUT.AFP** and writes PDF output to file **/tmp/output.pdf**.

```
//AOPBATCH JOB ...
//TRANSFRM EXEC PGM=AOPBATCH,
// PARM='/afp2pdf -o /tmp/output.pdf "'//''HLQ.INPUT.AFP''"'
//STDOUT DD SYSOUT=*
//STDERR DD SYSOUT=*
```

Transform and print data sets

This example shows how to transform data and print the output from the transform in a subsequent step.

In the first step, transform **ps2afp** reads PostScript input from MVS data set **HLQ.INPUT.PS** and writes AFP output to MVS data set **HLQ.OUTPUT.AFP**, where **HLQ** represents the high-level qualifier; for example, your TSO or RACF user ID.

In the second step, the **AOPPRINT** JCL procedure is used to print the output from the transform to the printer named **myprinter**, which is defined in the Printer Inventory. For more information about **AOPPRINT**, see Chapter 5, “Printing using the **AOPPRINT** JCL procedure” on page 153.

```
//AOPBATCH JOB ...
//TRANSFRM EXEC PGM=AOPBATCH,PARM='/ps2afp -o //DD:OUTPUT //DD:INPUT'
//INPUT DD DSN=HLQ.INPUT.PS,DISP=SHR
//OUTPUT DD DSN=HLQ.OUTPUT.AFP,DISP=(NEW,CATLG,DELETE),
// DCB=(RECFM=VBM,LRECL=32756,BLKSIZE=32760),
// SPACE=(CYL,(1,1))
//STDOUT DD SYSOUT=*
//STDERR DD SYSOUT=*
//PRINT EXEC AOPPRINT,PRINTER='myprinter'
//SYSIN DD DSN=HLQ.OUTPUT.AFP,DISP=SHR
```

Exit values

AOPBATCH returns the exit code of the spawned process. If **AOPBATCH** cannot execute the program, it returns 4.

Chapter 7. Printing from VTAM applications

The NetSpool component of Infoprint Server lets you print jobs from Virtual Telecommunications Access Method applications, such as Customer Information Control System (CICS) or Information Management System (IMS), without changing the applications. To use NetSpool effectively, you should understand:

- The data streams that NetSpool supports, including transparent data
- Differences between printing with NetSpool and printing on Systems Network Architecture (SNA) printers
- End-of-file processing in NetSpool
- Page formatting in NetSpool
- E-mail support

Data-stream support

NetSpool accepts these types of VTAM data streams:

- SNA character string (SCS) data over a logical unit (LU) type 1 session.
- 3270 data over an LU type 3 or LU type 0 session.
- Any printable data. For this type of data, your administrator must select the NetSpool **None** formatting option in the Printer Inventory.

NetSpool converts the data stream that it receives as input into one of these types of output data streams, according to the type of NetSpool formatting the administrator has selected in the printer definition in the Printer Inventory:

- Line data stream: If the administrator selects the **Convert to line** formatting option, NetSpool creates EBCDIC variable-length records, each record starting with an American Standards Association (ASA) carriage-control character.
- PCL data stream: If the administrator selects the **Convert to PCL** formatting option, NetSpool creates an ASCII text data stream with embedded PCL commands.
- Binary data stream: If the administrator selects the **None** formatting option, NetSpool creates variable-length records without converting or translating any controls or data.

NetSpool uses default page-formatting values defined by the administrator if the SCS data stream does not contain Set Horizontal Format or Set Vertical Format commands.

These sections and books describe SCS and 3270 data streams in more detail:

- Appendix C, “NetSpool support for SCS code points” on page 197 describes the code points that NetSpool supports for the SCS data stream.
- Appendix D, “NetSpool support for 3270 data streams code points” on page 207 describes the code points that NetSpool supports for the 3270 data stream.
- *SNA—Sessions Between Logical Units* describes the SCS data stream.
- *3270 Information Display System Data Stream Programmer's Reference* describes the 3270 data stream.
- *IBM 3270 Kanji Data Streams* describes double-byte character set (DBCS) SCS and 3270 data streams.

Transparent data support (SCS data stream)

The Transparent (TRN) control in SCS data streams identifies the start of a transparent data stream. NetSpool supports transparent data by including TRN controls and transparent data in line data output. NetSpool increases the output column and line position by the number of bytes of transparent data, as specified in a TRN control.

NetSpool provides two installation exits that let the administrator customize the processing of transparent data for all or selected printer names:

- The Beginning of File exit (APIPPTD1) adds transparent data to the beginning of a data set.
- The Transparent Data Control exit (APIPPTD2) inspects, changes, or deletes transparent data whenever it occurs in the data stream.

Double-byte character set (DBCS) support

NetSpool supports DBCS data in both SCS and 3270 data streams when it converts data streams to line data. NetSpool does *not* support DBCS data when it converts data streams to PCL data.

In an SCS data stream, NetSpool supports these controls, which identify DBCS strings:

- Shift Out and Shift In controls
- Set Attribute controls, with the Character Set attribute

In a 3270 data stream, NetSpool supports these controls and orders, which identify DBCS strings:

- Shift Out and Shift In controls
- Set Attribute (SA) orders, with the Character Set attribute
- Start Field Extended (SFE) orders with the Character Set attribute
- Modify Field (MF) orders with the Character Set attribute

In place of these controls and orders, NetSpool inserts Shift Out and Shift In line-data controls where necessary in line data output.

Tip: To prevent unwanted blanks in DBCS output, specify the PRMODE=SOSI2 parameter on the OUTPUT JCL statement that NetSpool uses to allocate data sets for the printer name.

Binary data support

The administrator can create a printer definition that specifies that NetSpool should treat input data as binary data. NetSpool writes binary data to the output data set, in variable length records, without examining or converting the data stream.

The administrator can specify the record size and record format (VB, VBA, or VBM) to use in outputting binary data to the spool.

NetSpool does not process TRN controls in binary data.

Data-stream restrictions

For SCS data streams, NetSpool does *not* support these codes:

- Function Management (FM) headers

NetSpool cannot handle FM headers because it does not expect FM data requests that it receives to be formatted. NetSpool rejects any request that contains an FM header with an SNA sense code of function error (X'10030000'), indicating an unsupported function.

- Some SCS commands.

For more information, see Appendix C, “NetSpool support for SCS code points” on page 197.

For 3270 data streams, NetSpool supports only these codes:

- Orders in the basic function set, as described in *SNA—Sessions Between Logical Units*.
- Shift Out and Shift In controls.
- Set Attribute (SA), Set Field Extended (SFE), and Modify Field (MF) orders, with the Character Set attribute. NetSpool ignores other attributes of the SA, SFE, and MF orders. For more information, see Appendix D, “NetSpool support for 3270 data streams code points” on page 207.

NetSpool rejects other orders in a 3270 data stream with an SNA sense code of function error (X'10030000'), indicating an unsupported function. Note that the Write Structured Fields (WSF) order is not included in the basic function set and, therefore, is not supported.

NetSpool does not reject unsupported commands or orders in binary data.

Data encryption and compression

Encrypted or compressed data sent to NetSpool are decrypted and decompressed as they arrive at the z/OS system where NetSpool is running. The data remains unencrypted and uncompressed during processing and after placement on the job entry subsystem (JES) spool.

Differences from SNA network printing

You might notice differences in these areas when sending output from VTAM application programs to NetSpool instead of to an SNA network printer:

- Notification of printing

When you send output to an SNA network printer, a positive response from the printer means that the data has been printed successfully. However, when you send output to NetSpool, a positive response from NetSpool means only that NetSpool has successfully created a JES output data set.

- Data-set printing

An SNA-network printer prints each VTAM print request separately. However, NetSpool combines several print requests into one output data set. In the printer definition for each printer in the Printer Inventory, the administrator can select the criteria that NetSpool uses when it combines print requests into one output data set.

- Deferred printing

When you print output on an SNA network printer, each print request is printed immediately. However, JES or the system operator might defer the printing of data sets that NetSpool creates until system resources are available.

- Printer sharing

Because an SNA network printer usually has a session limit of 1, your output is usually the only output that is printed on that printer. However, because JES

supports printer sharing, data sets from other users might be printed on the same printer. An installation can print distribution information on the header pages to aid in distributing output.

End-of-file processing

Printing in a JES environment requires that NetSpool keep all related print data together in an output data set on the JES spool. This ensures that related print data is printed in the correct order and is not interleaved with other output.

For printing in the SNA network, the concept of a data set is not necessary. An application starting a session with a printer gains exclusive control of that printer for the duration of the session. Therefore, data always prints in the correct order and is not interleaved with any other application's print output.

In contrast, when you print in a JES environment, the sending application is not guaranteed exclusive control of the printer. Between two successive data sets from one application, nothing prevents the printing of data sets from other applications. If the first attempt to print a data set fails, and a later retry succeeds, two successive data sets from the same application could even be printed in reverse order. Therefore, to guarantee that data belonging together gets printed in the correct order, without other data between sets, NetSpool batches that data into one data set.

Thus, for printing in a JES environment, NetSpool must determine where one data set should end and the next one should begin. NetSpool receives print data from VTAM applications as a stream of request units (RUs). The SNA architecture defines two groupings of RUs that are of interest:

- A *chain* consists of one or more RUs.
- A *bracket* consists of all of the RUs in one or more related chains.

To help determine when end-of-file occurs, NetSpool provides these end-of-file rules for defining data sets:

- End-of-bracket (the default rule)
- End-of-session
- End-of-chain
- End-of-file indicated by a specified string of data in the file's last end-of-chain request
- End-of-file indicated by the expiration of a timer

The administrator can specify which end-of-file rule to use in the printer definition for each printer in the Printer Inventory. If NetSpool does not correctly determine the end of your data sets, ask the administrator to specify another end-of-file rule.

Page formatting for SCS data streams

In some cases, SCS data streams used in LU type 1 sessions depend on a page format that has been preset for the SNA network printer. To simulate this page format, NetSpool lets the administrator specify page-formatting values in the Printer Inventory. The administrator can specify default values for line length, page length, margins, and tabs. If the administrator does not specify a default page-formatting value, NetSpool uses hard-coded default page-formatting values.

If the print data stream contains the SCS commands Set Horizontal Format (SHF) and Set Vertical Format (SVF), the page-formatting values in these commands take effect immediately and remain in effect for all subsequent print data sets on the same session. If no SHF or SVF command occurs in the print data stream, NetSpool uses the default page-formatting values. For more information about the SCS SHF and SVF commands, see Appendix C, “NetSpool support for SCS code points” on page 197.

The page-formatting values are:

MPP=*linelength* | 80

Specifies the maximum presentation position, that is, the line length. Specify zero or any integer from 1 through 255, inclusive. Zero, the default, uses the device line length, which NetSpool implements as 80 columns.

LM=*leftmargin* | 1

Specifies where the left margin starts. Specify zero or any integer from 1 through MPP, inclusive. Zero, the default, uses the architectural default of column 1.

RM=*rightmargin* | 0

Specifies where the right margin starts. Specify zero or a number from the left margin (LM) to the line length (MPP), inclusive. Zero, the default, uses the architectural default of the MPP value.

HT=*(tab1,tab2 ...)* | 0

Specifies positions of horizontal tabs. The first tab is always the same as the left margin (LM) value and does not need to be specified. Each tab can be zero or greater than or equal to LM, or less than RM. Zero, the default, is valid and ignored. The application data stream can add additional tab stops but cannot remove default tab stops.

MPL=*pagelength* | 1

Specifies the number of the maximum presentation line, that is, the maximum number of lines to be printed on the page. Specify zero or any integer from 1 through 255, inclusive. Zero, the default, uses the architectural default of 1 line.

TM=*topmargin* | 1

Specifies where the top margin (also channel 1) starts. The top margin is also used as the line number for Select Vertical Channel 1. Specify zero or any integer from 1 through the page length (MPL), inclusive. Zero, the default, uses the architectural default of line 1.

BM=*bottommargin* | 0

Specifies where the bottom margin starts. Specify zero or any integer from top margin (TM), which is also channel 1, to the page length (MPL), inclusive. Zero, the default, uses the architectural default of MPL. A bottom margin of 1 suppresses automatic form feed when the application spaces past the bottom margin.

VT=*(tab1,tab2, ...)* | 0

Identifies the position of vertical tabs (also channels 2–12). The first tab is always the same as the top margin value (TM) and does not need to be specified. The first 11 vertical tabs are also used as the line numbers for Select Vertical Channel 2 through 12. Each tab must be either zero or greater than or equal to top margin (TM), which is also Channel 1, and less than or equal to the bottom margin (BM), inclusive. Zero, the default, is valid and ignored. The application data stream can add additional tab stops but cannot remove default tab stops.

If the default page-formatting values are not appropriate for all target printers, the administrator must define appropriate values in one or more printer definitions in the Printer Inventory.

Tips:

1. In the ISPF panels that the administrator uses to create a printer definition, the fields for setting SCS page-formatting values are under the heading **SCS Conversion**.
2. The SCS page-formatting values in the printer definition do *not* apply when NetSpool formats 3270 input data. Instead, when NetSpool formats 3270 data, it uses page-formatting information that is specified in the 3270 data stream, in the Write Control Character (WCC).
3. When the administrator selects the NetSpool **Convert to PCL** formatting option, the administrator can also specify page orientation (portrait and landscape), page density, and line density values for both SCS and 3270 data streams in the Printer Inventory. For SCS data streams only, the administrator can also request that NetSpool automatically determine the appropriate page orientation on a page-by-page basis. In the ISPF panels, the fields for setting these page-formatting values are under the heading **NetSpool PCL Conversion**.

Sending output to an e-mail destination

You can send VTAM application output to an e-mail destination instead of to a printer, or you can send output to *both* an e-mail destination and to a printer. Your administrator can specify the e-mail address list of the recipients in the printer definition for the e-mail destination in the Printer Inventory, or you can specify the address list in an alias file that your administrator defines to z/OS UNIX sendmail. For more information, see “Specifying the e-mail address list in an alias file” on page 112.

The e-mail has these characteristics:

- Each output data set is an e-mail attachment in a separate e-mail. The name of the attachment is the PLU name of the VTAM application that created the output, with an extension that indicates the type of data in the file. For example, txt indicates text format data and pdf indicates PDF data.
- The subject of the e-mail is the value specified for the title in the printer definition or, if none is specified, the member name of the NetSpool startup procedure.
- The sender is the user ID of the user who started NetSpool at the domain of the z/OS system. E-mail recipients should not reply to this user ID.

Chapter 8. Printing from Windows systems

With Infoprint Server, you can print from your Windows 98, Windows NT, Windows 2000, Windows XP, and Windows Millennium Edition (Me) system to any printer defined in the Infoprint Server Printer Inventory.

You can use these methods to submit a print request:

- Any Windows application that supports printing, such as a word processor or a viewer application
- Windows **print** command (available on Windows NT, 2000, and XP)
- Windows LPR command (available on Windows NT, 2000, and XP)

Table 10 summarizes the tasks related to submitting a print request and refers you to the section that describes the task. Required tasks are required by all users. Optional tasks are required only if the listed condition applies.

Table 10. Printing from Windows systems

Task	Condition	See page
Determining the print submission protocol	Optional: To print from a Windows application or with the print command	169
Installing Infoprint Port Monitor for Windows	Optional: To use the Infoprint Port Monitor	170
Adding a z/OS printer to your Windows system	Optional: To print from a Windows application or with the print command	171
Customizing the AFP Printer Driver	Optional: To use the AFP driver and change driver options	177
Sending a file to an e-mail destination	Optional: To send files to an e-mail destination instead of to a printer	177
Printing files	Required	178
Uninstalling the Infoprint Port Monitor for Windows	Optional: To remove the Infoprint Port Monitor	180

Determining the print submission protocol

To print from a Windows application or with the **print** command, you must determine which protocol you want to use to submit your print request to Infoprint Server. Your administrator must customize Infoprint Server to use each of these protocols. Therefore, consult your administrator to determine which protocols you can use in your installation.

- Infoprint Port Monitor: The Infoprint Port Monitor for Windows is a program that automatically directs files to Infoprint Server running on the z/OS system. The Infoprint Port Monitor runs on Windows 98, NT, 2000, XP, and Me systems.
- Server Message Block (SMB) protocol: SMB is the standard printing protocol provided with Windows systems. Infoprint Server supports the SMB protocol on Windows 98, NT, and 2000 systems.
- Internet Printing Protocol (IPP): IPP lets you print over the Internet from a Windows IPP client. Windows 2000 and Windows XP provide an IPP client.

These protocols support different print functions and have different limitations as summarized in Table 11.

Table 11. Comparison of Windows printing protocols

Function supported	Infoprint Port Monitor	SMB	IPP
Specify job attributes during printing	Yes ¹	No	Yes ²
Obtain print job status	No ³	Yes ⁴	No
Define a Windows shared printer	Yes	Yes	No
<ol style="list-style-type: none"> 1. You can specify any job attributes described in Chapter 3, "Using job attributes" on page 85. 2. You can specify any IPP job attributes. However, Infoprint Server supports only the copies, document-name, and priority job attributes. 3. The Infoprint Port Monitor returns an error if Infoprint Server cannot accept the job. However, after Infoprint Server accepts a print job, it does not report any further status. 4. When the Windows job status window is open, z/OS system performance might be degraded. 			

Installing Infoprint Port Monitor for Windows

Note: The installation instructions in this chapter are current as of publication. If the product files are subsequently updated, the installation instructions might change. For the latest installation instructions, visit the IBM Printing Systems Web site at: <http://www.ibm.com/printers/>

Before you begin

Make sure that these software requirements are met:

- Microsoft Windows 98, Windows NT (Version 4.0 with Service Pack 6, or a higher version), Windows 2000, Windows XP, or Windows Me is required.
- Microsoft TCP/IP must be configured and operational.
- Microsoft Internet Explorer 3.x (or later) is required to view Port Monitor online help. You can download the Internet Explorer from the Microsoft Web site at: <http://www.microsoft.com/ie/>
- If you have Infoprint Manager Select installed on your Windows system, Infoprint Manager Select should be at the latest level.

Note: If an earlier version of the Infoprint Port Monitor is installed on your Windows system, do *not* uninstall it before you install Infoprint Port Monitor Version 2.0.0. Infoprint Port Monitor Version 2.0.0 automatically replaces the previous version and also saves your Windows printers and your Infoprint port configuration. However, future updates to the Infoprint Port Monitor might require that you first uninstall the Infoprint Port Monitor. If so, documentation provided with the update will tell you the procedure.

Steps for installing Infoprint Port Monitor for Windows

To install the Infoprint Port Monitor for Windows:

1. Download the Infoprint Port Monitor from one of these locations:
 - Download this z/OS file: /usr/lpp/Printsrv/win/En_US/aopwin.exe.

Use a file transfer program, such as ftp, and download the file in binary. To do this, you need an account on the z/OS system where Infoprint Server is installed.

- Download from the Web at: <http://www.ibm.com/printers/download.html>.
If your Web browser is Microsoft Internet Explorer and you select to run or open the port monitor from its current location, the port monitor is automatically installed and you can skip the remaining steps.

The examples in the next step assume that you downloaded file aopwin.exe to Windows directory c:\zostemp.

-
2. If the Infoprint Port Monitor was not automatically installed in the previous step:
 - a. Run **aopwin** to install the Infoprint Port Monitor. For example, in the Run dialog, enter:
c:\zostemp\aopwin

The installation requires you to restart your Windows system.
 - b. Delete file aopwin.exe from your workstation. For example, delete
c:\zostemp\aopwin.exe.
-

Result: You can now add one or more z/OS printers to your Windows system as local Windows printers. Follow the instructions in “Adding a local printer and configuring the Infoprint Port Monitor for Windows” on page 172, or follow the more detailed instructions that are displayed after you install the Infoprint Port Monitor. A shortcut to the detailed instructions is placed on your Windows desktop during the install of the Infoprint Port Monitor.

When you upgrade the Infoprint Port Monitor to Version 2.0.0, your printers and Infoprint ports are saved. Therefore, you do not need to add the printers again or reconfigure the Infoprint ports. If you defined a Windows shared printer, you might want to select the **Unattended port** option, which was introduced in Infoprint Port Monitor Version 2.0.0. For instructions, see “Steps for reconfiguring an Infoprint port on Windows NT, Windows 2000, and Windows XP systems” on page 175.

Adding a z/OS printer to your Windows system

Before you can print on a z/OS printer, you must define the printer to your Windows system. Use one of these methods:

- If you are using SMB protocol for printing, see *z/OS Distributed File Service SMB Administration* for information about how to add a z/OS printer.
- If you are using the Infoprint Port Monitor for printing, add the printer to your Windows system as a local printer. However, if your Windows administrator has already defined the printer as a Windows shared printer, add the shared printer to your system as a Windows network printer.
- If you are using the IPP protocol for printing, define the printer as an Internet printer.

Adding a local printer and configuring the Infoprint Port Monitor for Windows

Before you begin

Before you add a printer, ask your Infoprint Server administrator for this information:

- The host name or the IP address of the z/OS system where Infoprint Server is running.
- The port number on the z/OS system at which Infoprint Server is listening. The port is usually 515.
- The name of the printer to use. This is the name your administrator used when the printer was defined to Infoprint Server.
- The name of the printer driver to use.

The printer driver converts your documents to a format that the printer understands. This driver might be available online, or the Windows administrator might give it to you on a diskette or CD-ROM.

The AFP Printer Driver converts your documents to AFP format for printing on IBM AFP printers. You can download the AFP Printer Driver, as well as other printer drivers, at no charge from the Web at <http://www.ibm.com/printers/download.html>.

If either the PCL to AFP transform or the PostScript to AFP transform is installed on the z/OS system, you can use a PCL or PostScript driver instead of the AFP driver.

- If you plan to use the AFP driver, the model number and resolution of the AFP printer.

Steps for adding a printer as a local printer

Use the Windows Add Printer Wizard to add a printer, and do these special steps, which occur in different orders on different Windows systems:

1. When the Add Printer Wizard asks you to select a port:

- a. Add an Infoprint port. Add a separate Infoprint port, with a unique name, for each z/OS printer to which you want to print.

Windows 98 and Me systems: Select the predefined **Infoprint Port** port from the list of available ports.

If you have already added a printer at the Infoprint port, select the Infoprint port but do *not* configure it as described in the next step. Instead, after you finish adding the printer, add another Infoprint port as described in “Steps for adding another Infoprint port on Windows 98 and Windows Me systems” on page 173.

Windows NT, 2000, and XP systems: For each printer, add a new Infoprint port and configure it. To add an Infoprint port in the Add Printer Wizard, select **Add Port**.

- b. Configure the Infoprint port.

Windows 98 and Me systems: After you select the Infoprint port, select **Configure Port** in the Add Printer Wizard.

Windows NT, 2000, and XP systems: After you select **Add Port**, the Infoprint Port Configuration dialog is displayed automatically.

On the Infoprint Port Configuration dialog:

- 1) Enter values in the **Host Name** and **Host Port** fields.
- 2) Select **Refresh Printer Selection List**.
- 3) Select the name of the printer from the list.

- 4) Select **Options** to display a screen where you can specify Infoprint Server job attributes. The default is that these attributes apply to every job you send to this printer. On the Infoprint Server Options dialog:
 - In the **Separator Sheet** box, fill in the information that you want to appear on the cover sheet printed before each job. Whether a field is printed depends on how your administrator has configured the separator sheet.
 - In the **Job Attributes** field, specify any of the job attributes described in Chapter 3, “Using job attributes” on page 85 (optional). Separate attributes with spaces.

Example: To specify a title for the separator page or a subject for an e-mail, and 2 copies of each printed document, enter:
title-text="description of contents" copies=2
 - If you want to specify different attributes for some documents, select the **Prompt for attributes when printing** check box.

Note: If you plan to define the printer as a Windows shared printer, do *not* select the **Prompt for attributes when printing** option because the Infoprint Server Options dialog is displayed only on the Windows system where the Infoprint Port Monitor is installed.
- 5) Select **Unattended port** if other users might print on the printer at this port. If you select this option, the Infoprint Port Monitor does not present error messages in pop-up windows on this Windows system and wait for replies. (On Windows NT, Windows 2000, and Windows XP systems, error messages are displayed in the Windows Event Log on the user's system.)
- 6) Select **OK**.

-
2. When the Add Printer Wizard asks you to select a printer driver, do these steps if you want to select the AFP Printer Driver:
 - a. Select **Have Disk**.
 - b. On the next panel, type the location of the Windows directory in which you installed the driver files (for example, d:\afpdriver) and select **OK**.
 - c. Select the model number of the z/OS printer.

If the model number is not on this list, select **IBM AFP nnn**, where *nnn* is the resolution of the printer. Then, change the printer characteristics as described in step 3, under “Customizing the AFP Printer Driver” on page 177.

-
3. **Windows NT, 2000, and XP systems:** When the Add Printer Wizard asks you whether you want to share the printer, select the **share** option if you want other users to share this Windows printer.
-

Steps for adding another Infoprint port on Windows 98 and Windows Me systems

After you add a second z/OS printer to your Windows 98 and Windows Me systems, you must add another Infoprint port for the printer and configure the port:

1. Open the Printers folder.

2. In the Printer window, right-click the printer icon for the printer you just added. Then select **Properties**.
3. In the Properties notebook, select the **Details** tab.
4. In the Details tab, select **Add Port**.
5. In the Add Port window, select **Other** and select **Infoprint Port Monitor** as the type of port. Then select **OK**.
6. Type a name for the new port, for example Infoprint-2. Use a name that is not already used for any other port.
7. In the Infoprint Port Configuration dialog, follow the instructions in the help for the dialog. Then select **OK**.
8. In the Details tab, you see the new port selected. Select **Apply**.
9. Select the **General** tab. Select **Print Test Page** (optional). Then select **OK**.

Steps for reconfiguring an Infoprint port on Windows 98 and Windows Me systems

You must reconfigure the Infoprint port if you want to print on a different printer, change separator sheet information, or change Infoprint Server job attributes:

1. Open the Printers folder.
2. In the Printer window, right-click the printer icon for the printer whose port you want to reconfigure. Then select **Properties**.
3. In the Properties notebook, select the **Details** tab.
4. In the Details tab, select **Port Settings**.
5. In the Infoprint Port Configuration dialog:
 - a. Select **Options** if you want to change information for the printer's separator sheet or job attributes.
 - b. Verify that values in the **Host Name** and **Host Port** fields are correct.
 - c. To select a new printer, select **Refresh Printer Selection List** and select the name of the printer from the list.
 - d. Do *not* select the **Unattended port** option. This option only is useful for printers defined as Windows shared printers on Windows NT, Windows 2000, and Windows XP systems.

e. Select **OK**.

6. In the Details tab of the Properties window, select **OK**.

Steps for reconfiguring an Infoprint port on Windows NT, Windows 2000, and Windows XP systems

You must reconfigure the Infoprint port if you want to print on a different printer, change separator sheet information, change Infoprint Server job attributes, or change the setting of the **Unattended port** option:

1. Open the Printers folder or the Printers and Faxes folder.

2. In the Printer window, right-click the printer icon for the printer whose port you want to reconfigure. Then select **Properties**.

3. In the Properties notebook, select the **Port** tab.

4. In the Ports tab, select **Configure Port**.

5. In the Infoprint Port Configuration dialog:

- a. Select **Options** if you want to change information for the printer's separator sheet or job attributes.
 - b. Verify that values in the **Host Name** and **Host Port** fields are correct.
 - c. To select a new printer, select **Refresh Printer Selection List** and select the name of the printer from the list.
 - d. Select **Unattended port** if other users might print on the printer at this port. If you select this option, the Infoprint Port Monitor does not present error messages in pop-up windows on this Windows system and wait for replies. (Error messages are always displayed in the Windows Event Log on the user's system.)
 - e. Select **OK**.
-

6. In the Ports tab of the Properties window, select **OK**.

Adding a network printer

If your Windows administrator has defined the z/OS printer as a shared printer in your Windows network:

1. Ask your Windows administrator for the name assigned to the printer.

2. Do the standard Windows procedures to add the z/OS printer as a network printer.

Note: If the Windows administrator defines a printer as shared, individual users cannot be prompted for attributes when printing.

Adding an Internet printer

Before you begin

Ask your Infoprint Server administrator for this information:

- The Uniform Resource Identifier (URI) of the printer.

The URI of a printer defined in the Printer Inventory has this format:

`http://host:port/servlet/IPPServlet/printername`

host The host name or IP address of the z/OS system.

port The port number where the IPP server is listening. The default is that the IPP server listens at port 631. Ask your administrator the port number to use.

printer_definition_name
The name of the printer definition in the Printer Inventory.

For example:

`http://myzoshost:631/servlet/IPPServlet/myprinter`

Be careful to note the exact spelling of the URI. Uppercase and lowercase letters are *not* equivalent.

- The manufacturer and model number of the printer.
- The name of the printer driver to use.

The printer driver converts your documents to a format that the printer understands. This driver might be available online, or your administrator might give it to you on a diskette or CD-ROM.

The AFP Printer Driver converts your documents to AFP format, which lets you print on IBM AFP printers. You can download the AFP Printer Driver at no charge from the Web at <http://www.ibm.com/printers/download.html>. If you want to use the AFP driver, you need to know the model number and resolution of the AFP printer.

If either the PCL to AFP transform or the PostScript to AFP transform is installed on the z/OS system, you can use a PCL or PostScript driver instead of the AFP driver.

Steps for defining a printer as an Internet printer on Windows 2000 and Windows XP systems

Use the standard Windows procedure to add a printer, and do these special steps:

1. When the Add Printer Wizard asks you whether to install the printer as a local printer or a network printer, select **Network printer**. On Windows XP, select **A network printer, or a printer attached to another computer**.
2. When the Add Printer Wizard asks you how to connect, select **Connect to a printer on the Internet**. Enter the URI of the printer in the **URL** field.
3. When the Add Printer Wizard asks you whether to install the printer driver, select **OK**.

While Windows is installing the printer driver, the Add Printer Wizard returns to the screen where you entered the URI. For some time, it might seem that nothing is happening. Do *not* cancel the job. Wait for the Add Printer Wizard to go on to the next screen.

Customizing the AFP Printer Driver

The AFP Printer Driver for Windows, which you can download from <http://www.ibm.com/printers/download.html>, creates AFP output for printing on IBM AFP printers. If you use the AFP Printer Driver, you can change default printing options and specify printer characteristics.

To configure the AFP Printer Driver:

1. In the Windows Printer directory, highlight the icon for the printer.

2. Do one of these, depending on your Windows system:
 - In Windows 98, from the File menu, select **Properties**. Then select the **Paper** and **Options** tabs of the notebook.
 - In Windows NT or Windows 2000, from the File menu, select **Document Defaults** and **Properties**.

3. Specify the default printing options and printer characteristics. To specify these printing options, select **Inline Form Definition** from either the **Options** tab (Windows 98) or from the Document Defaults dialog (Windows NT or 2000):
 - Duplex printing (printing on 2 sides of the paper)
 - Printing of an overlay (electronic form)
 - Paper source on the printer (input tray)

For faster printing of large files, consider turning on the **Use substitution table** option (Windows 98) or turning off the **Print text as graphics** option (Windows NT or 2000). This causes the driver to create a smaller output file. First, make sure that your printer can do font substitution. Also, note that if you use True-Type fonts, the document might not print with exact fidelity. For better resolution, you can try changing the **Output Fidelity** options on the driver.

Usually, the printer characteristics, such as whether the printer can do font substitution and handle compressed images, and the supported clip limits, are already set correctly. However, if the name of the AFP Printer Driver is **IBM AFP *nnn***, where *nnn* is the resolution of your printer, you might need to change the printer characteristics to match those of the printer. Ask your administrator for the needed information, or consult the printer documentation.

Sending a file to an e-mail destination

When you submit a print request, you can send the file to an e-mail destination instead of to a printer. When you send a file to an e-mail destination, your administrator can specify the e-mail address list of the recipients in the printer definition in the Printer Inventory, or you can specify the address list in an alias file

that your administrator defines to z/OS UNIX sendmail. For information, see “Specifying the e-mail address list in an alias file” on page 112.

The e-mail has these characteristics:

- The file is an attachment to the e-mail. The name of the attachment is the name specified in the **sysout-dataset-name** job attribute. If this attribute is not specified, the name of the attachment is the last 8 characters of the file name. A pound sign (#) is used in the file name instead of any character that the system does not allow in a file name on the JES spool. For example, a slash or a period is replaced with a pound sign.
The attachment name contains an extension that indicates the type of data in the file. For example, txt indicates text data and pdf indicates PDF data.
- The subject of the e-mail is the value specified to the Port Monitor in the **title-text** job attribute. If none is specified, the subject is the title your administrator specified in the Allocation section of the printer definition. If no title is specified in the printer definition, the subject is the job name. If you use the LPR command, you can specify the job name in **-J** option.
- The sender is the Windows user ID of the user who submitted the print request.
- You cannot receive replies to the e-mail.

Printing files

You can use these methods to print a file:

- Print function on any Windows application that supports printing. See “Printing from a Windows application”.
- Windows **print** command. See “Using the print command” on page 179.
- Windows LPR command. See “Using the LPR command” on page 179.

Printing from a Windows application

To print from a Windows application, use the print function that the application provides and select the Windows printer that you defined in “Adding a z/OS printer to your Windows system” on page 171.

If you are using the Infoprint Port Monitor and selected **Prompt for attributes when printing** when you customized the Infoprint Port Monitor, you see the Infoprint Server Options dialog. (If the Infoprint Port Monitor is busy transmitting a file or if your Windows system is busy, you might not see this dialog immediately.) In the **Job Attributes** field, you can add any of the attributes described in Chapter 3, “Using job attributes” on page 85, or change any of the default attributes that you entered when you added the printer.

For example, if you want to print three copies of this file on one side of the paper, change the **Job Attributes** field to read:

```
copies=3 duplex=no
```

Only IBM AFP printers support the **duplex** attribute. VTAM-controlled printers and some IPP-enabled printers do not support the **copies** attribute. If you send the file to an e-mail destination, only one copy is sent.

Note: If the Windows printer is defined as a shared printer, do *not* select the **Prompt for attributes when printing** option because the Infoprint Server Options dialog is displayed only on the Windows system where the Infoprint Port Monitor is installed.

Using the print command

Some Windows systems provide a **print** command, which you can use to print on a printer you defined in “Adding a z/OS printer to your Windows system” on page 171. To use the **print** command, you or your Windows administrator must define the z/OS printer as a Windows shared printer. The **print** command lets you print a file directly without using a Windows application that supports printing.

You can specify these command and options when you print using Infoprint Server:

```
print /d:\servername\print_share file
```

servername

Specifies the name of the Windows server on which the z/OS printer was defined as a Windows shared printer. The Windows server can be your own Windows system or a different Windows system.

print_share

Specifies the name of the Windows printer.

file

Specifies the location and name of the file you want to print. You can include multiple files on one command line.

Using the LPR command

Some Windows systems provide an LPR command, which you can use to print on any printer defined to Infoprint Server in the Printer Inventory. The LPR command lets you print a file directly without using a Windows application that supports printing.

To use the LPR command, the administrator must have configured the Infoprint Server LPD to listen at port 515. If the Infoprint Server LPD listens at a different port, use the **print** command instead. To use the **print** command, you must configure the Infoprint Port Monitor to submit print requests to the port at which the Infoprint Server LPD is listening.

You can specify these command and options when you print using Infoprint Server:

```
LPR -S server -P printer -J job file
```

server

Specifies the IP address or host name of the z/OS system on which Infoprint Server is running.

printer

Specifies the name of the printer definition in the Printer Inventory. This name is case-sensitive.

job

Specifies a job name that is printed as the title on a separator page. Whether the title is printed depends on how the administrator has configured the printer's separator page. If the file is sent to an e-mail destination, this job name is used as the subject of the e-mail.

file

Specifies the name of the file you want to print or send to an e-mail destination.

Infoprint Server does *not* support or require these LPR options:

-C class

Infoprint Server does not support this option. It is ignored if specified.

-d

The LPR sends the data file first. Infoprint Server supports this option. However, IBM recommends that you do not specify it for large files or files that need to be transformed to another data format because it can hurt system performance.

-o *option*

Indicates the type of print file. This option is not required because Infoprint Server automatically detects the type of file.

-x Infoprint Server does not support this option.

Uninstalling the Infoprint Port Monitor for Windows

The instructions to uninstall the Infoprint Port Monitor are different for Version 1 and Version 2 of the port monitor. To determine the version installed on your system:

- **Windows 98, Windows NT, and Windows 2000 systems:**

1. From the Windows Control Panel, select **Add/Remove Programs**. If the Infoprint Port Monitor is listed, Infoprint Port Monitor Version 2.0.0 or later is installed.
2. If the Infoprint Port Monitor is not listed, select **Start→Programs**. If Infoprint Port Monitor is listed, Infoprint Port Monitor Version 1.0 is installed.

- **Windows Me and Windows XP systems:** Infoprint Port Monitor Version 2.0.0 is installed.

Note: When you upgrade the Infoprint Port Monitor for Windows to Version 2.0.0, do *not* uninstall the current version. When you upgrade to Version 2.0.0, the Infoprint Port Monitor saves your existing Windows printers defined at Infoprint ports but *only* if you have not uninstalled the Infoprint Port Monitor.

Steps for uninstalling Infoprint Port Monitor Version 2.0.0 and later

To uninstall Infoprint Port Monitor Version 2.0.0 and later versions, use the standard Windows uninstall procedure:

1. From the Windows Control Panel window, select **Add/Remove Programs**.
2. Follow the instructions in the Add/Remove Program Properties dialog to remove the Infoprint Port Monitor.

Steps for uninstalling Infoprint Port Monitor Version 1.0 on Windows 98 Systems

To uninstall Infoprint Port Monitor Version 1.0 on Windows 98 systems:

Note: Do *not* run the unInstallShield program provided with Infoprint Port Monitor Version 1.0 because this program does not work.

1. Remove port monitor data from the registry:
 - a. Start the registry editor using one of these methods:
 - Enter `regedit` in an MS-DOS Command Prompt window. To open an MS-DOS Command Prompt window, select **Start** on the task bar, then select **Programs→MS-DOS Command Prompt**.
 - Enter `regedit` in a Run dialog. To open a Run dialog, select **Start** on the task bar, then select **Run**.

- b. Select the **+** icon to expand **HKEY_LOCAL_MACHINE** and then expand **SOFTWARE**.
 - c. Delete the location of registry data for the version of the port monitor you installed:
 - If you installed a recent version of the port monitor, expand **IBM** and then delete **Infoprint Port Monitor**.
 - If you installed an early version of the port monitor, expand **IBM Printing Systems** and then delete **OS/390 Port**.
 - d. Select the **—** icon to collapse **SOFTWARE**.
 - e. Expand **System**, **CurrentControlSet**, **Control**, **Print**, and then **Monitors**.
 - f. Delete the name of registry data for the version of the port monitor you installed:
 - If you installed a recent version of the port monitor, delete **Infoprint Printer Port**.
 - If you installed an early version of the port monitor, delete **OS/390 Printer Port**.
 - g. Close the registry editor.
-

2. Restart your workstation.

3. Erase **ipmon95.dll** and **ip39095.dll** from the Windows system directory (typically **c:\windows\system**).

Note: You cannot erase these files until you have updated your registry and restarted your workstation.

4. Remove the port monitor's install directory and the files in it:

- a. Start Windows Explorer: select **Start** on the task bar, then select **Programs** and select **Windows Explorer**.
 - b. Delete the port monitor's install directory for the version of the port monitor you installed:
 - If you installed a recent version of the port monitor, delete the default directory, **c:\Infoprint**, or the directory you specified during installation.
 - If you installed an earlier version of the port monitor, delete the default directory, **c:\os390**, or the directory you specified during installation.
 - c. Close Windows Explorer.
-

5. Remove the port monitor from Programs:

- a. Select **Start** on the task bar, then select **Settings** and select **Taskbar**.
- b. Select the **Start Menu Programs** tab.
- c. Select **Remove**.
- d. Expand **Programs**, if necessary.
- e. Remove the name of the port monitor for the version you installed:
 - If you installed a recent version of the port monitor, select **Infoprint Port Monitor** and then select **Remove**.

- If you installed an earlier version of the port monitor, select **OS/390 Printer Port** and then select **Remove**.
- f. Select **OK**.

Steps for uninstalling Infoprint Port Monitor Version 1.0 on Windows NT and Windows 2000 systems

To uninstall Infoprint Port Monitor Version 1.0 on Windows NT and Windows 2000 systems:

Note: Do *not* run the unInstallShield program provided with Infoprint Port Monitor Version 1.0 because this program does not work.

1. Remove port monitor data from the registry:
 - a. Start the registry editor using one of these methods:
 - Enter regedt32 in an MS-DOS Command Prompt window. To open an MS-DOS Command Prompt window, select **Start** on the task bar, then select **Programs→MS-DOS Command Prompt**.
 - Enter regedt32 in a Run dialog. To open a Run dialog, select **Start** on the task bar, then select **Run**.
 - b. Double-click the + icon to expand **HKEY_LOCAL_MACHINE** and then expand **SOFTWARE**.
 - c. Delete the location of registry data for the version of the port monitor you installed:
 - If you installed a recent version of the port monitor, expand **IBM**, select **Infoprint Port Monitor**, select **Edit** on the menu bar, and then select **Delete**.
 - If you installed an early version of the port monitor, expand **IBM Printing Systems**, select **OS/390 Port**, select **Edit** on the menu bar, and then select **Delete**.
 - d. Double-click the — icon to collapse **SOFTWARE**.
 - e. Expand **SYSTEM**, **CurrentControlSet**, **Control**, **Print**, and then **Monitors**.
 - f. Delete the name of registry data for the version of the port monitor you installed:
 - If you installed a recent version of the port monitor, select **Infoprint Printer Port**, select **Edit** on the menu bar, and then select **Delete**.
 - If you installed an early version of the port monitor, select **OS/390 Printer Port**, select **Edit** on the menu bar, and then select **Delete**.
 - g. Close the registry editor.
-
2. Stop the Spooler service:
 - a. Select **Start** on the task bar and then select **Settings→Control Panel**.
 - b. Double-click **Services**.
 - c. Select **Spooler** and then select **Stop**.
-
3. Erase ipmonnt.dll and ip390nt.dll from the Windows system directory (typically c:\winnt\system32).

Note: You cannot erase these files until you have stopped the spooler service or shut down and restarted your workstation.

4. Start the Spooler service:
 - a. Select **Start** on the task bar and then select **Settings→Control Panel**.
 - b. Double-click **Services**.
 - c. Select **Spooler** and then select **Start**.

 5. Remove the port monitor's install directory and the files in it:
 - a. Start Windows NT Explorer: select **Start** on the task bar and then select **Programs→Windows NT Explorer**.
 - b. Delete the port monitor's install directory for the version of the port monitor you installed:
 - If you installed a recent version of the port monitor, delete the default directory, c:\Infoprint, or the directory you specified during installation.
 - If you installed an earlier version of the port monitor, delete the default directory, c:\os390, or the directory you specified during installation.
 - c. Close Windows NT Explorer.

 6. Remove the port monitor from Programs:
 - a. Select **Start** on the task bar and then select **Settings→Taskbar**.
 - b. Select the **Start Menu Programs** tab.
 - c. Select **Remove**.
 - d. Expand **Programs**, if necessary.
 - e. Remove the name of the port monitor for the version you installed:
 - If you installed a recent version of the port monitor, select **Infoprint Port Monitor** and then select **Remove**.
 - If you installed an earlier version of the port monitor, select **OS/390 Printer Port** and then select **Remove**.
 - f. Select **OK**.
-

Chapter 9. Printing from remote non-Windows systems

This chapter describes how to print from non-Windows workstations where TCP/IP is installed. For detailed information about the syntax of the commands described in this chapter, see the documentation for each remote system.

Tips:

1. Infoprint Server might ignore some command options. For example, it ignores command codes that contain information for printing on separator pages if your administrator has not configured the separator pages to show this information.
2. Infoprint Server accepts commands that are sent from any port on the sending host.
3. If Infoprint Server Transforms is installed on the z/OS system, your data streams can be automatically transformed into the format accepted by the printer. PCL, PDF, PostScript, and SAP data streams can be transformed to AFP format. AFP data streams can be transformed to PCL, PDF, or PostScript format. If XML Extender is installed, your XML data streams can be automatically transformed to AFP format.

Submitting a print request

You can use the LPR command to submit a print request. From an AIX system, you can also use the **enq** command.

Before you begin: Before you use an LPR or **enq** command, ask your administrator for:

- The host name or IP address of the z/OS system on which Infoprint Server is running.
- The name of the printer definition created for the printer. This name is case-sensitive. You must specify this name as the name of the printer or print queue.
- The name of a suitable printer driver for the z/OS printer if you print from an OS/2 system.

The OS/400 LPR command and the AIX **enq** command let you specify Infoprint Server job attributes, which are described in Chapter 3, “Using job attributes” on page 85.

For more information about how to submit an LPR or **enq** command from a particular system, see:

- “Printing from an AIX workstation” on page 187
- “Printing from an OS/2 workstation” on page 188
- “Printing from a remote OS/390 or z/OS system” on page 189
- “Printing from a VM or z/VM system” on page 189
- “Printing from an OS/400 system” on page 189

After receiving a print request, Infoprint Server returns either an error message or a job identifier. The job identifier indicates that Infoprint Server has accepted the print request. You can use the job identifier to query the status of the print request or to cancel the print request.

Sending a file to an e-mail destination

When you use the LPR or **enq** command, you can send the file to an e-mail destination instead of to a printer. When you send a file to an e-mail destination, your administrator can specify the e-mail address list of the recipients in the printer definition for the e-mail destination in the Printer Inventory, or you can specify the address list in an alias file that your administrator defines to z/OS UNIX sendmail. For information, see “Specifying the e-mail address list in an alias file” on page 112.

The e-mail has these characteristics:

- The file is an attachment to the e-mail. The name of the attachment is the name specified in the **sysout-dataset-name** job attribute. If this attribute is not specified, the name of the attachment is the last 8 characters of the file name. A pound sign (#) is used in the file name instead of any character that the system does not allow in a file name on the JES spool. For example, a slash or a period is replaced with a pound sign.
The name of the attachment contains an extension that indicates the type of data in the file. For example, **txt** indicates text data and **pdf** indicates PDF data.
- The subject of the e-mail is the title specified in the **title-text** job attribute or the title specified on the LPR command. If none is specified, the title is the value your administrator specified in the Allocation section of the printer definition. If none is specified, the subject is the job name.
- The sender is the user who submitted the print request.
- You cannot receive replies to the e-mail.

Querying a print request

You can use the **lpq** command to query the names, locations, and descriptions of printers and to query the status of a print request. From an AIX system, you can also use the **qstat** command.

When you query the status of a print request, Infoprint Server returns one of these states:

pending	The file is waiting to print. Tip: Because JES3 cannot distinguish job states, in a JES3 environment Infoprint Server can return pending for files that have been selected for processing or held on the JES spool.
processing	The file has been placed on the JES spool and selected for processing. It can be: <ul style="list-style-type: none">• Being transmitted to a local area network (LAN) printer or to a print server• Printing
held	The file is held on the JES spool and cannot print for one of these reasons: <ul style="list-style-type: none">• The user specified hold=true when submitting the job. Tip: JES3 does not recognize a job that is held for this reason and returns pending.• The operator held the job.
completed	The file has been processed successfully. It remains on the JES spool for one of these reasons:

- Other files in the job are still being processed. The file will be removed from the spool after all files in the job have been processed.
- Your administrator has specified that files should be retained after transmission to a LAN printer or to a print server. The file will be removed from the spool when the retention period expires.

failed

Processing has failed. The file remains on the JES spool for one of these reasons:

- Transmission to a LAN printer, to a print server, or to the z/OS UNIX sendmail function has failed. Your administrator has specified that files should be retained after transmission. The file will be removed from the spool when the retention period expires.
- An error occurred during processing. The file is held.

purged

The file was deleted before printing.

Printing from an AIX workstation

To print from an AIX system, you must configure a remote queue. During configuration of the remote queue, do these steps:

1. Specify the host name or IP address of the z/OS system as the host name.

-
2. Specify the name of the printer definition as the queue name.

-
3. Specify **BSD** as the type of print spooler.

-
4. Specify the -X option for the remote queue in the **backend** option under the queue device name in the **/etc/qconfig** file. The -X option lets you specify Infoprint Server job attributes in the **-o** option on the **enq** command.

If you print large files, especially files that will be transformed from one format to another on the z/OS system, also specify the -T option to increase the time-out value. The default time-out value is 90 seconds. Depending on the size of your files, you might need to specify a time-out value of a few minutes. For extremely large jobs, you might need to specify an hour or more.

Also specify the -C option, which sends the control file first. This can improve system performance, especially when you print large files.

This **backend** option specifies a time-out value of 5 minutes in the -T option:

```
backend=/usr/lib/lpd/rembak -X -T 5 -C
```

-
5. After you change the **/etc/qconfig** file, delete the **/etc/qconfig.bin** file. Then, use these commands to stop and restart the queue daemon:

```
stopsrc -s qdaemon
startsrc -s qdaemon
```

After you configure the remote queue, specify the name of the remote queue on the **enq**, **lpr**, or **lp** command. For example:

`enq -P remotequeue -o "XAOPattribute=value..." file`

`lpr -P remotequeue file`

`lp -d remotequeue file`

-d remotequeue

Specifies the name of the remote queue.

-P remotequeue

Specifies the name of the remote queue.

-o "XAOPattribute=value..." | -o 'X attribute=value...'

Specifies any job attributes you want to use to print the job. If there are any spaces or special characters in the list of job attributes, surround the string with single or double quotation marks.

For a list of job attributes that you can specify, see Chapter 3, “Using job attributes” on page 85.

If there are errors in the list of attributes and you use the **XAOP** form of the prefix, the job is rejected. If you use the **X** form of the prefix, the job is processed without the attributes.

Limitation: The **lpr** and **lp** commands do *not* support the **-o** option.

file

Specifies the name of the file you want to print.

Printing from an OS/2 workstation

You can print from an IBM OS/2 system that uses TCP/IP version 3.0, either from an OS/2 application or by using the drag-and-drop method of printing. Before printing, you must configure TCP/IP and define the z/OS printer to the OS/2 system.

To define a printer:

1. Select an LPD port as the output port.
2. Change the properties of the output port:
 - a. Specify the host name or IP address of the z/OS system as the LPD server.
 - b. Specify the name of the printer definition in the Printer Inventory as the LPD printer. This name is case-sensitive.
 - c. (Optional) Specify your system name and user name in the print source fields.
3. Select a printer driver that is suitable for the type of printer. For example, select a PostScript driver for a printer that can print PostScript data streams. The printer driver creates output in a format that the printer understands.

If the printer is an IBM AFP printer, you can select a generic text driver. However, if your installation has installed either the PCL to AFP transform or the PostScript to AFP transform on the z/OS system, you can get higher-quality output if you select a PCL or PostScript driver.

To print on the z/OS printer from the command line, use the **lpr** command. For example:

`lpr -p printername -s hostaddress filename [-b]`

-p *printername*

Specifies the name of the printer definition in the Printer Inventory. This name is case-sensitive.

-s *hostaddress*

Specifies the IP address or host name of the z/OS host on which Infoprint Server is running.

filename

Specifies the name of the file you want to print.

-b

Specifies that the document contains data that must be interpreted as binary. Specify this option to print a document in PCL, PDF, PostScript, SAP, or AFP format.

Printing from a remote OS/390 or z/OS system

To print from a remote z/OS system, use the LPR command from a TSO session:

LPR '*filename*' (P *printername* AT *hostaddress* TITLE *title*

filename

Specifies the name of the file you want to print.

P *printername*

Specifies the name of the printer definition in the Printer Inventory. This name is case-sensitive.

AT *hostaddress*

Specifies the IP address or host name of the z/OS host on which Infoprint Server is running.

TITLE *title*

Specifies a title that can be printed on a separator page if your administrator has configured the separator page to do so. If the file is sent to an e-mail destination, the title becomes the subject of the e-mail.

Printing from a VM or z/VM system

To print from a VM or z/VM system, use the LPR command. For example:

LPR *filename* (PRINTER *printername* HOST *host_address*

filename

Specifies the file name, file type, and file mode of the file you want to print.

PRINTER *printername*

Specifies the name of the printer definition in the Printer Inventory. This name is case-sensitive.

HOST *hostaddress*

Specifies the IP address or host name of the z/OS host on which Infoprint Server is running.

Printing from an OS/400 system

The most convenient way to print from an OS/400 system is to do these steps:

1. Define a remote print queue for a printer that your administrator has defined to Infoprint Server, if the administrator has not already done so. To do this:
 - a. Enter the CRTOUTQ command on the OS/400 command line.
 - b. Fill in the panels:

Output queue

The name you want to give to the remote output queue.

Remote system

The host name or IP address of the z/OS system on which Infoprint Server is running.

Remote print queue

The name of a printer definition that your administrator has created.

Writers to autostart

1

Connection type

*IP

Destination type

*OTHER

Host print transform

Specify *NO to print the AFP data stream. Specify *YES to print the Systems Network Architecture (SNA) character string (SCS) data stream.

Manufacturer type and model

*WSCST

Workstation customizing object

QSYS/QWPDEFAULT

Destination options

Specify any job attributes you want to use to print the job. Use one of these two formats:

'XAOPattribute=value...'

'Xattribute=value...'

Surround the entire value, including the X or XAOP prefix and the list of attributes, in single quotation marks, as shown. If any of the attribute values contains special characters, surround the value in double quotation marks.

For a list of job attributes that you can specify, see Chapter 3, "Using job attributes" on page 85.

If there are errors in the list of attributes and you use the XAOP form of the prefix, the job is rejected. If you use the X form of the prefix, the job is processed without the attributes.

-
2. Submit the file you want to print on the remote print queue exactly as you would submit it on a local print queue.
-

3. To start a remote printer writer, enter:

STRRTWTR *outputqueue*

The name of the remote output queue is *outputqueue*. The remote printer writer takes files from the output queue and sends them to the printer.

4. To end the remote printer writer, enter:

```
ENDWTR outputqueuename
```

You can also use the LPR command to send files to z/OS. The files must already be on the spool, in a queue that does not have a printer writer started against it. You do not define a remote output queue, but you specify many of the same options for the LPR command as you would for a remote output queue. You can also specify job attributes on the LPR command. For example:

```
LPR RMTSYS(hostname) PRTQ('printqueue') FILE(filename)  
  JOB(jobid/userid/jobname) SPLNBR(n) MFRTYPMDL(*WSCST)  
  WSCST(QSYS/QWPDEFAULT) TRANSFORM(*NO)  
  DESTOPT('XAOPattribute=value...')
```

RMTSYS(*hostname*)

Specifies the host name of the z/OS host on which Infoprint Server is running.

PRTQ('printqueue')

Specifies a print queue defined in a printer definition. If the print queue name contains lowercase characters, you must surround it in single or double quotation marks.

FILE(*filename*)

Specifies the file name of the file you want to print.

JOB(*jobid/userid/jobname*)

Identifies the job by number, user ID of the job owner, and name. You can determine this information by entering the WRKOUTP command to view a list of spooled files.

SPLNBR(*n*)

Specifies the spool file number of the file you want to print. You can determine the spool file number by viewing a list of spooled files.

MFRTYPMDL(*WSCST)

Specifies that the manufacturer, type, and model of the printer are as defined in the workstation customizing object.

WSCST(QSYS/QWPDEFAULT)

Specifies the workstation customizing object as QSYS/QWPDEFAULT.

TRANSFORM({*YES|*NO})

Specifies whether to transform the data to ASCII format. Specify *YES for SCS data. Specify *NO for AFP data.

DESTOPT('XAOP*attribute=value...*')

DESTOPT('X*attribute=value...*')

Specifies any job attributes you want to use to print the job. Surround the entire value, including the X or XAOP prefix and the list of attributes, in single quotation marks, as shown. If any of the attribute values contains special characters, surround the value in double quotation marks.

For a list of job attributes that you can specify, see Chapter 3, “Using job attributes” on page 85.

If there are errors in the list of attributes and you use the XAOP form of the prefix, the job is rejected. If you use the X form of the prefix, the job is processed without the attributes.

When you print a text document from an OS/400 system using a workstation customization object of QSYS/QWPDEFAULT, Infoprint Server might not recognize the data format as text. Either Infoprint Server rejects the job or data does not print as expected.

This problem occurs because the host print transform and workstation customization object QSYS/QWPDEFAULT on the OS/400 system inserts an initial null byte into the print file before sending it to Infoprint Server. The null byte prevents Infoprint Server from recognizing the data format as text.

To correct this problem, you can use the source statements below to create a workstation customization object that does not insert an initial null byte. These statements are the same as for the QSYS/QWPDEFAULT object, but with :INITPRT DATA='00'X. removed. For information about how to create a customization object, see *OS/400 Workstation Customization Programming V4R3*.

```
:WSCST DEVCLASS=TRANSFORM.  
:TRNSFRMTBL.  
:SPACE  
  DATA ='20'X.  
:CARRTN  
  DATA ='0D'X.  
:FORMFEED  
  DATA ='0C'X.  
:LINEFEED  
  DATA ='0A'X.  
:EWSCST.
```

Printing from a Novell NetWare client

You can use standard printing procedures to submit jobs to Infoprint Server from clients connected to a Novell NetWare 3.x, 4.x, or 5.x server. Your Novell administrator must create a NetWare print queue on the NetWare server and configure the queue to use the LPD protocol to send print jobs to the Infoprint Server LPD on the z/OS system. You must know the name of the NetWare print queue to submit jobs.

Appendix A. Job attributes and JCL parameters valid for different printer types

Table 12 shows which job attributes and JCL parameters Infoprint Server can validate for a selected printer. Infoprint Server checks the value you specify in these job attributes and JCL parameters against the supported values the administrator specifies in the printer definition.

Table 12. Job attributes and JCL parameters validated for the printer

Job attribute	JCL parameter	Value validated for printer
address-text	ADDRESS	No
building-text	BUILDING	No
carriage-control-type	RECFM	No
chars	CHARS	No
copies	COPIES	Yes
department-text	DEPT	No
document-codepage	none	No
document-format	none	Yes
document-type	none	No
duplex	DUPLEX	Yes
filter-options	none	No
form-definition	FORMDEF	No
forms	FORMS	Yes
hold	HOLD OUTDISP (JES2 only)	No
input-tray	none	Yes
input-tray-number	INTRAY	No
jes-priority	PRTY	No
name-text	NAME	No
output-bin	none	Yes
output-bin-number	OUTBIN	No
overlay-back overlay-front	OVERLAYB OVERLAYF	No
page-definition	PAGEDEF	No
print-error-reporting	DATAACK	Yes
print-queue-name	PRTQUEUE	No
printer-ip-address	DEST=IP	No
resource-library	USERLIB	No
room-text	ROOM	No
shift-out-shift-in	PRMODE	No
sysout-dataset-name	DSNAME	No
sysout-job-id	none	No
sysout-job-name	job name	No

Table 12. Job attributes and JCL parameters validated for the printer (continued)

Job attribute	JCL parameter	Value validated for printer
table-reference-characters	DCB OPTCD=J TRC	No
title-text	TITLE	No
x-image-shift-back x-image-shift-front	OFFSETXB OFFSETXF	No
y-image-shift-back y-image-shift-front	OFFSETYB OFFSETYF	No

Appendix B. JCL parameters and corresponding job attributes

Table 13 lists parameters of the OUTPUT and DD JCL statements and the Infoprint Server job attributes that correspond to them. Some job attributes, such as **document-format**, do not have corresponding JCL parameters. You can specify job attributes in a batch application when you use the AOPPRINT JCL procedure and when you use the Print Interface subsystem.

Table 13. JCL parameters and corresponding job attributes

JCL parameter	Job attribute	See page
ADDRESS	address-text	87
BUILDING	building-text	88
CHARS	chars	88
COPIES	copies	90
DATAACK	print-error-reporting	100
DCB OPTCD=J	table-reference-characters	105
DEPT	department-text	90
DEST=IP	printer-ip-address	101
DSNAME	sysout-dataset-name	103
DUPLEX	duplex	92
FORMDEF	form-definition	94
FORMS	forms	95
HOLD ¹ OUTDISP (JES2 only)	hold	95
INTRAY	input-tray input-tray-number	95
job name (on JOB statement)	sysout-job-name	104
NAME	name-text	97
OFFSETXB	x-image-shift-back	106
OFFSETXF	x-image-shift-front	107
OFFSETYB	y-image-shift-back	107
OFFSETYF	y-image-shift-front	108
OUTBIN	output-bin output-bin-number	98
OVERLAYB	overlay-back	99
OVERLAYF	overlay-front	99
PAGEDEF	page-definition	100
PRMODE	shift-out-shift-in	103
PRTQUEUE	print-queue-name	101
PRTY	jes-priority	97
RECFM	carriage-control-type	88
ROOM	room-text	102
TITLE	title-text	105
TRC	table-reference-characters	105

Table 13. JCL parameters and corresponding job attributes (continued)

JCL parameter	Job attribute	See page
USERLIB	resource-library	102
none	document-codepage	90
none	document-format	91
none	document-type	92
none	filter-options	93
none	sysout-job-id	104
1. When you use the Print Interface subsystem, you cannot specify the HOLD parameter on the DD JCL statement. However, you can specify the OUTDISP parameter on the OUTPUT JCL statement.		

Appendix C. NetSpool support for SCS code points

The NetSpool component of Infoprint Server converts the Systems Network Architecture character stream (SCS) for a logical unit (LU) type 1 printer into one of these data streams:

- Line data stream: If the administrator selects the **Convert to line** formatting option, NetSpool creates EBCDIC variable-length records, each record starting with an American Standards Association (ASA) carriage-control character.
- PCL data stream: If the administrator selects the **Convert to PCL** formatting option, NetSpool creates an ASCII text data stream with embedded PCL commands.

NetSpool returns these SNA sense codes for errors found in the SCS data stream:

- SNA sense code of function error (X'10030000') for undefined and unsupported code points.
- SNA sense code of parameter error (X'10050000') for supported code points with invalid parameters or without all parameters available in the same chain.
- SNA sense code of data error (X'10010000') for invalid characters in a DBCS string.

NetSpool passes all other unspecified code points to JES as text data to be printed.

For information about SCS data streams, see:

- *SNA - Sessions Between Logical Units*
- *IPDS and SCS Technical Reference*

Table 14 describes the SCS code points that are supported and unsupported when NetSpool creates line data or PCL data streams.

Table 14. SCS code points

Control code	EBCDIC	Name	Line support	PCL support
BEL	X'2F'	Bell function	Ignore	Ignore
BS	X'16'	Back space	Yes	Yes
CR	X'0D'	Carriage return	Yes	Yes
EBS	X'36'	Expanded back space	Yes	Yes
ENP	X'14'	Enable presentation	Ignore	Ignore
ESP	X'E1'	Expanded space	Yes	Yes
FF	X'0C'	Form feed	Yes	Yes
GE	X'08'	Graphic escape	Yes	Yes
HT	X'05'	Horizontal tab	Yes	Yes
IT	X'39'	Indent tab	Ignore	Ignore
IR	X'33'	Index return	Yes	Yes
INP	X'24'	Inhibit presentation	Ignore	Ignore
IFS	X'1C'	Interchange file separator	Yes	Yes
IGS	X'1D'	Interchange group separator	Yes	Yes

Table 14. SCS code points (continued)

Control code	EBCDIC	Name	Line support	PCL support
IRS	X'1E'	Interchange record separator	Yes	Yes
IUS	X'1F'	Interchange unit separator	Yes	Yes
LF	X'25'	Line feed	Yes	Yes
NL	X'15'	New line	Yes	Yes
NULL	X'00'	Null	Ignore	Ignore
PP	X'34xxnn'	Presentation position (see Table 15 on page 201)	Yes	Yes
PPM	X'2BD2...'	Page presentation media (see Table 16 on page 202)	Ignore	Yes
RFF	X'3A'	Required form feed	Yes	Yes
RNL	X'06'	Required new line	Yes	Yes
RSP	X'41'	Required space	Yes	Yes
SA	X'28xxxx'	Set attribute (see Table 23 on page 203)	Yes	Ignore/Error
SBS	X'38'	Subscript	Ignore	Yes
SCI	X'2BDx'	Set chain image	Ignore	Ignore
SGEA	X'2BC8'	Set graphic error action	Ignore	Ignore
SHF	X'2BC1xx'	Set horizontal format (see Table 24 on page 204 and Table 25 on page 205)	Yes	Yes
SHY	X'CA'	Syllable hyphen	Yes	Yes
SI	X'0F'	Shift in ¹	Yes	Error
SLD	X'2BC602xx' or X'2BC601'	Set line density	Ignore	Yes
SLP	X'04C1'	Select left platen	Ignore	Ignore
SME	X'046x'	Select magnetic encoder	Error	Error
SO	X'0E'	Shift out ¹	Yes	Error
SOF	X'2BC3'	Start of format	Yes	Yes

Table 14. SCS code points (continued)

Control code	EBCDIC	Name	Line support	PCL support
SPD	X'2BD20229' or X'2BD20429xxxx' Tip: X'2BD20229' indicates to set the print density to the default setting. 'xxxx' specifies the number of characters per inch. This is a 2-byte binary number. The first byte is X'00' and the second byte is the print density hex value.	Set print density	Ignore	Yes
SPS	X'09'	Superscript	Ignore	Yes
SRP	X'04C2'	Select right platen	Ignore	Ignore
SSR	X'0450'	Secure string ID reader	Error	Error
STT	X'2BD1xx'	Set translate table	Ignore	Ignore
SUB	X'3F'	Substitute	Yes	Yes
SVF	X'2BC2'	Set vertical format (see Table 26 on page 205 and Table 27 on page 206)	Yes	Yes
TRN	X'35'	Transparent	Yes	Yes
UBS	X'1A'	Unit backspace	Ignore	Ignore
VCS	X'04xx' Tip: 'xx' is a 2-byte order. Byte two defines the function: <ul style="list-style-type: none"> • 50 Magnetic stripe reader - error • 60, 61 Magnetic stripe writer - error • 7A-7C Vertical channels 10 through 12 - skip to channel • 81-89 Vertical channels 01 through 09 - skip to channel • C1, C2 Select Left/Right Platten - ignore • Other - error 	Vertical channel select	Yes	Yes
VT	X'0B'	Vertical tab	Yes	Yes

Table 14. SCS code points (continued)

Control code	EBCDIC	Name	Line support	PCL support
WUS	X'23'	Word underscore	Yes	Yes
<ul style="list-style-type: none"> • Yes—Supported • Ignore—NetSpool removes the control code from the data stream and does not report an error. • Error—Undefined or unsupported code point-function or parameter error 				

Note:

1. Shift Out (SO) indicates the start of a string of double-byte character set (DBCS) data. Shift In (SI) indicates the end. Valid characters in the DBCS string are X'4040' and any pair of bytes, each in the range X'41' to X'FE'. NetSpool rejects invalid characters and DBCS strings that do not complete in the same chain with an SNA sense code of data error (X'10010000').

Presentation Position command

The Presentation Position command (X'34xxnn') is a 3-byte command that moves the print head to a new horizontal or vertical position. The movement can be absolute or relative to the current column or line. Byte 2 is the function code. Byte 3 is a relative or absolute line or column number. NetSpool supports this command when it converts the input data stream to either a line data or a PCL data stream.

The movement can be absolute or relative to the current column or line. There are variations of movement with or without erase that are intended for display devices only. "Erase to new position and return to former position" commands are ignored. "Move with erase" creates the same output as "move without erase." Movement to the right inserts blank columns in the line. Movement to the left causes the current line to be written and a new blank line set up for overstrike starting at the specified column. Movement to a higher line number causes the current line and some blank lines to be written. Movement to a lower line number causes the current line, a form feed, and some number of blank lines to be written.

Table 15. Presentation Position X'34xxnn'

Byte 1	Byte 2 (xx) function code	Function parameter	Function parameter action (line data and PCL)	Byte 3 (nn) value parameter
X'34'	X'C0'	Absolute, Horizontal (no erase)	Move Presentation Position and do not erase	1-byte binary number denoting either absolute or relative column number
	X'C1'	Absolute, Horizontal (erase, return)	NetSpool ignores this function code	
	X'C2'	Absolute, Horizontal (erase, move)	Erase line to and move to new Presentation Position	
	X'C4'	Absolute, Horizontal (no erase)	Move Presentation Position and do not erase	
	X'C5'	Absolute, Horizontal (erase, return)	NetSpool ignores this function code	
	X'C6'	Absolute, Horizontal (erase, move)	Erase Column to new Presentation Position and move to new Presentation Position	
	X'C8'	Absolute, Horizontal (no erase, move)	Move Presentation Position and do not erase	
	X'C9'	Absolute, Horizontal (erase, return)	NetSpool ignores this function	
	X'4A'	Absolute, Horizontal (erase, move)	Erase line through, and move to new Presentation Position	
	X'4C'	Absolute, Horizontal (erase, move)	Move Presentation Position and do not erase	
	X'4D'	Absolute, Horizontal (erase, return)	NetSpool ignores this function	
	X'4E'	Absolute, Horizontal (erase, move)	Erase column through new Presentation Position and move to new Presentation Position	

Presentation Page Media control

The Presentation Page Media control (X'2BD2') lets you select paper sources and specify simplex or duplex printing. NetSpool supports this control only when it converts the input data stream to a PCL data stream.

Table 16. Presentation Page Media (2BD2)

Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	Byte 8	Byte 9	Byte 10	Byte 11	Byte 12
X'2B'	X'D2'	NN count byte	X'48'	X'00'	X'00'	FC forms control	SD source drawer	DDO offset	DD destination drawer	X'00'	DX simplex or duplex

Table 17. Presentation Page Media (2BD2) nn (count byte)

nn (count byte)	Description	PCL command
X'02'	Select tray 1	<ESC>&I1H
X'05'	Use FC byte to select paper menu/source	
X'06'	Use FC byte to select source drawer	
X'0A'	Use FC, SD, and DX bytes	

Table 18. Presentation Page Media (2BD2) FC (forms control byte)

FC (forms control byte)	Description	PCL command
X'00'	Ignore	
X'01'	Use SD byte	
X'02'	Select auxiliary tray	<ESC>&I4H
X'03' X'04'	Select auxiliary tray - manual feed	<ESC>&I2H
X'FF'	Select tray 1	<ESC>&I1H
other values	Use SD byte	

Table 19. Presentation Page Media (2BD2) SD (source drawer byte)

SD (source drawer byte)	Description	PCL command
X'00'	Ignore	
X'01' X'FF'	Select tray 1	<ESC>&I1H
X'02'	Select tray 2	<ESC>&I5H
X'03'	Select tray 3	<ESC>&I7H
X'04'	Select auxiliary feeder	<ESC>&I2H
X'05'	Select tray 4	<ESC>&I8H
X'06'	Select tray 5	<ESC>&I9H
other values	Use tray 1	<ESC>&I1H

Table 20. Presentation Page Media (2BD2) DDO (destination drawer offset)

DDO (destination drawer offset)	Description	PCL command
X'00'	Ignore	
other values	Offset	<ESC>&l1T

Table 21. Presentation Page Media (2BD2) SD (destination drawer byte)

SD (destination drawer byte)	Description	PCL command
X'00'	Ignore	
X'01'	Select default output bin	<ESC>&l1G
X'02'	Select output bin 2	<ESC>&l2G
X'03'	Select output bin 3	<ESC>&l3G
X'04'	Select output bin 4	<ESC>&l4G
other values	Select default output bin	<ESC>&l1G

Table 22. Presentation Page Media (2BD2) DX (destination drawer duplex)

DX (destination drawer duplex)	Description	PCL command
X'00'	Ignore	
X'01'	Simplex	<ESC>&l0S
X'02'	Duplex	<ESC>&l1S
X'03'	Tumble duplex	<ESC>&l2S

Tip: The “l” in the PCL commands above is actually a lowercase “L”.

SCS Set Attribute control

Table 23. SCS Set Attribute (X'28xxyy')

Byte 1	Byte 2 function parameter	Function description	Byte 3 value	Line data support	PCL support
X'28'	X'00'	Reset characteristics	X'00'	Reset to single-byte character set	NetSpool ignores this function
	X'41'	Highlighting	any value	NetSpool ignores this function	NetSpool ignores this function
	X'42'	Color	any value	NetSpool ignores this function	NetSpool ignores this function

Table 23. SCS Set Attribute (X'28xyy') (continued)

Byte 1	Byte 2 function parameter	Function description	Byte 3 value	Line data support	PCL support
	X'43'	Character Set	X'00'	Reset character set to single-byte character set.	Error
			X'F8'	Start of double-byte character set data.	Error
			other values		Error
				Error	
	X'C2'	Field Outlining	any value	NetSpool ignores this function	NetSpool ignores this function

Table Note: Set Attribute X'2843F8' indicates the start of double-byte character set (DBCS) data. Set Attribute X'284300', X'280000', or end-of-chain indicates the end. Valid characters in the DBCS string are X'4040' and any pair of bytes, each in the range X'41' to X'FE'. NetSpool rejects invalid characters with an SNA sense code of data error (X'10010000').

NetSpool converts SA code points that indicate the start and end of a DBCS string into Shift Out (SO) and Shift In (SI) line-data controls. NetSpool converts valid SCS code points in the DBCS string to the appropriate line-data controls, delimited by SI and SO line-data controls.

Set Horizontal Format (SHF)

Table 24 describes the parameters that can be used with the SHF code point.

Table 24. Set Horizontal Format parameters

SHF parameter	Name	Range	NetSpool default
MPP	Maximum line length	1–255	80 (The administrator can change the default in the printer definition in the Printer inventory.)
LM	SCS left margin (position of first column)	1–MPP	1 (The administrator can change the default in the printer definition in the Printer inventory.)

Table 24. Set Horizontal Format parameters (continued)

SHF parameter	Name	Range	NetSpool default
RM	SCS right margin (position of last column)	LM-MPP	MPP (The administrator can change the default in the printer definition in the Printer inventory.)
HT	SCS horizontal tab settings		

SHF can be converted to a sequence of PCL Left Margin and PCL Right Margin commands. The horizontal tab settings, if specified, will be saved for use with the SCS Horizontal Tab control.

The definition in the Content column of Table 25 explains what values you should use in the corresponding column positions.

Table 25. Set Horizontal Format

Bytes	Content
1–2	X'2BC1'
3	Count of bytes after byte 2. It must be in range of 1–255 (count includes itself).
4 (optional)	MPP <ul style="list-style-type: none"> • 0 means to leave the hardware default • 1–255 are valid line lengths in the columns
5 (optional)	LM <ul style="list-style-type: none"> • 0 means to leave the hardware default • 1–MPP are valid column positions
6 (optional)	RM <ul style="list-style-type: none"> • 0 means to leave the current MPP (hardware default or this command) • LM–MPP are valid column positions
7–257 (optional)	HT <ul style="list-style-type: none"> • 0 is ignored • LM–RM are valid column positions

Set Vertical Format (SVF)

Table 26 describes the parameters that can be used with the SVF code point.

Table 26. Set Vertical Format parameters

SVF parameter	Name	Range	NetSpool default
MPL	Maximum number of lines per page	1–255	1 (The administrator can change the default in the printer definition in the Printer inventory.)

Table 26. Set Vertical Format parameters (continued)

SVF parameter	Name	Range	NetSpool default
TM	SCS top margin (position of first line)	1–MPL	1 (The administrator can change the default in the printer definition in the Printer inventory.)
BM	SCS bottom margin	MPL (If not specified the current MPL is used. The default of 1 indicates that the page length is controlled by form feeds placed in the data stream.)	MPL (The administrator can change the default in the printer definition in the Printer inventory.)
VT	SCS vertical tab settings		

SVF can be converted to a sequence of PCL Top Margin and PCL Page Length commands. The vertical tab settings, if specified, will be saved for use with the SCS Vertical Tab or Vertical Channel Select control.

The definition in the Content column of Table 27 explains what values you should use in the corresponding column positions.

Table 27. Set Vertical Format convert to PCL

Bytes	Content
1–2	X'2BC2'
3	Count of bytes after byte 2. It must be in range of 1–255 (count includes itself).
4 (optional)	MPL or page length <ul style="list-style-type: none"> • 0 means to leave the hardware default • 1–255 are valid page lengths in lines
5 (optional)	TM and Channel 01 <ul style="list-style-type: none"> • 0 means to leave the hardware default • 1–MPL are valid line numbers
6 (optional)	BM <ul style="list-style-type: none"> • 0 means to leave the current MPL (hardware default or this command) • TM–MPL are valid line numbers
7–257 (optional)	VT (7–18 are also channels 02–12) <ul style="list-style-type: none"> • 0 is ignored • TM+1–BM are valid line numbers

Appendix D. NetSpool support for 3270 data streams code points

The NetSpool component of Infoprint Server converts 3270 data streams for logical unit (LU) type 0 and type 3 into one of these data streams:

- Line data stream: If the administrator selects the **Convert to line** formatting option, NetSpool creates EBCDIC variable-length records, each record starting with an American Standards Association (ASA) carriage-control character.
- PCL data stream: If the administrator selects the **Convert to PCL** formatting option, NetSpool creates an ASCII text data stream with embedded PCL commands.

Table 28, Table 29, and Table 30 on page 208 describe the code points that are supported for 3270 data streams.

For information about 3270 data streams, see:

- *IBM 3270 Information Display System Reference Summary*
- *IBM 3270 Information Display System 3274 Control Unit Description*
- *IBM 3270 Information Display System Data Stream Programmer's Reference*
- *IBM 3270 Kanji Data Streams*

Command codes

Only one command is allowed in each RU chain. The command must be the first byte of the RU chain.

Table 28 describes the code points that are supported for 3270 data streams.

Table 28. 3270 data stream command codes

Command code	EBCDIC	Name
W	X'F1'	Write
EW	X'F5'	Erase/Write
EWA	X'7E'	Erase/Write Alternate
EAU	X'6F'	Erase All Unprotected
Other command codes		Function not supported—returns SNA sense code X'1003000'

Control codes

The control codes have an EBCDIC value in the range of X'00' through X'3F'. Table 29 describes the code points that are supported for 3270 data streams and also explains if it is fully supported.

Table 29. 3270 data stream control codes

Control code	EBCDIC	Name	Line support	PCL support
CR	X'0D'	Carriage Return	Yes	Yes
EM	X'19'	End of Message	Yes	Yes
EUA	X'12'	Erase Unprotected to Address	Yes	Yes

Table 29. 3270 data stream control codes (continued)

Control code	EBCDIC	Name	Line support	PCL support
FF	X'0C'	Form Feed	Yes ¹	Yes ¹
GE	X'08'	Graphic Escape	Yes	Yes
IC	X'13'	Insert Cursor	Yes	Yes
MF	X'2C'	Modify Field (see Table 30)	Yes	Yes
NL	X'15'	New Line	Yes	Yes
PT	X'05'	Program Tab	Yes	Yes
RA	X'3C'	Repeat to Address	Yes	Yes
SA	X'28'	Set Attribute (see Table 30)	Yes	Yes
SBA	X'11'	Set Buffer Address	Yes	Yes
SF	X'1D'	Start Field	Yes	Yes
SFE	X'29'	Start Field Extended (see Table 30)	Yes	Yes
SI	X'0F'	Shift in	Yes	Error
SO	X'0E'	Shift out	Yes	Error
SYN	X'32'	SYN Character	Ignore	Ignore
Other control codes			Error	Error
Explanation of NetSpool support: <ul style="list-style-type: none"> • Yes: The control code is supported. • Ignore: NetSpool removes the control code from the data stream and does not report an error. • Error: NetSpool returns an SNA sense code X'1003000'. 				
1. The form feed (FF) control must occupy the first print position on a line. To put the FF control in the first position, place X'0C' after a Write Control Character, a NL control, or a CR control. The FF is printed as a space character.				

Attribute types

Table 30 describes the attribute types that are supported for 3270 data streams.

Table 30. 3270 data stream attribute types

Attribute type	EBCDIC	SFE, MF orders	SA order	Comments
Character Attribute Reset	X'00'	N/A	X	Sets character set attribute to single-byte character set (default).

Table 30. 3270 data stream attribute types (continued)

Attribute type	EBCDIC	SFE, MF orders	SA order	Comments
Character Set	X'43'	X	X	<p>When attribute value is X'00'-X'7F', character set attribute is set to single-byte.</p> <p>When attribute value is X'F8'-X'FE', character set attribute is set to double-byte. However, a value in this range is an error when converting to PCL.</p>
3270 Field Attribute	X'C0'	X	N/A	<p>Field attribute bit definitions supported:</p> <ul style="list-style-type: none"> • Bit 2 = B'0' Field is unprotected. • Bit 2 = B'1' Field is protected. • Bits 4,5 = B'11' Field is nonprintable. • Bits 4,5 Other settings are ignored. <p>All other bit definitions are ignored.</p>
Other Valid Attributes	X'41', X'42', X'45', X'46', X'C2'	X	X	Ignored. The default is no operation. Attributes are ignored.
Invalid Attributes		X	X	Function not supported. Returns SNA sense code X'1003000'.
N/A	The attribute type does not apply to the order.			
X	The attribute type does apply to the order.			

Appendix E. Accessibility

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, use software products successfully. The major accessibility features in z/OS let users:

- Use assistive technologies such as screen-readers and screen magnifier software.
- Operate specific or equivalent features using only the keyboard.
- Customize display attributes such as color, contrast, and font size.

Using assistive technologies

Assistive technology products, such as screen-readers, work with the user interfaces found in z/OS. Consult the assistive technology documentation for specific information when using it to access z/OS interfaces.

Keyboard navigation of the user interface

Users can access z/OS user interfaces using TSO/E or ISPF. For information about accessing TSO/E and ISPF interfaces, see *z/OS TSO/E Primer*, *z/OS TSO/E User's Guide*, and *z/OS ISPF User's Guide Volume I*. These books describe how to use TSO/E and ISPF, including the use of keyboard shortcuts or function keys (PF keys). Each book includes the default settings for the PF keys and explains how to modify their functions.

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Department 11PA Building 002S
PO Box 1900
Boulder CO 80301 USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee. The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Trademarks

The following terms appear in this publication and are either trademarks or registered trademarks of International Business Machines Corporation in the United States, in other countries, or both:

AFP
AIX
Application System/400
CICS
eNetwork
IBM
IBM @server
IMS
IMS/ESA
Infoprint
Intelligent Printer Data Stream
IP PrintWay
IPDS
Language Environment
MVS/ESA
NetSpool
OpenEdition
Operating System/2
OS/2
OS/390
OS/400
Print Services Facility
PrintWay
RACF
RETAIN
RS/6000
S/390
VTAM
WIN-OS/2

z/OS
z/OS.e
z/VM
zSeries

The following terms appear in this publication and are either trademarks or registered trademarks of subsidiaries of International Business Machines Corporation in the United States, in other countries, or both:

- Freelance is a trademark of Lotus Development Corporation. Lotus is a registered trademark of Lotus Development Corporation.

The following terms appear in this publication and are either trademarks or registered trademarks of other companies in the United States, in other countries, or both:

- Java is a registered trademark of Sun Microsystems, Inc.
- MCS is a registered trademark of Intel.
- Microsoft, Windows, and Windows NT are registered trademarks of Microsoft Corporation.
- UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, and service names may be trademarks or service marks of others.

Bibliography

This section lists books that might help you to configure and use Infoprint Server.

Infoprint Server

Title	Order number
<i>Infoprint Server Transforms Licensed Program Specifications</i>	G544-5797
<i>z/OS Infoprint Server Customization</i>	S544-5744
<i>z/OS Infoprint Server Introduction</i>	S544-5742
<i>z/OS Infoprint Server Messages and Diagnosis</i>	G544-5747
<i>z/OS Infoprint Server Migration</i>	G544-5743
<i>z/OS Infoprint Server Operation and Administration</i>	S544-5745
<i>z/OS Infoprint Server User's Guide</i>	S544-5746
<i>Infoprint Server for z/OS Implementation Redbook</i>	SG24-6234
<i>Infoprint XML Extender for z/OS</i>	S544-5855

Print Services Facility™ for OS/390

Title	Order number
<i>AFP Conversion and Indexing Facility: User's Guide</i>	S544-5285
<i>PSF for OS/390 & z/OS: Customization</i>	S544-5622
<i>PSF for OS/390 & z/OS: Diagnosis</i>	G544-5623
<i>PSF for OS/390 & z/OS: Download for OS/390</i>	S544-5624
<i>PSF for OS/390 & z/OS: Introduction</i>	G544-5625
<i>PSF for OS/390 & z/OS: Messages and Codes</i>	G544-5627
<i>PSF for OS/390 & z/OS: User's Guide</i>	S544-5630

Advanced Function Presentation (AFP)

Title	Order number
<i>IBM Printing Systems: Printer Information</i>	S544-5750
<i>IBM Printing Systems: Printer Summary</i>	S544-5749
<i>AFP: Programming Guide and Line Data Reference</i>	S544-3884
<i>IBM AFP Fonts: Font Summary for AFP Font Collection</i>	S544-5633
<i>IBM Data Stream and Object Architectures: Bar Code Object Content Architecture Reference</i>	S544-3766
<i>IBM Data Stream and Object Architectures: IOCA Reference</i>	SC31-6805
<i>IBM Page Printer Formatting Aid: User's Guide</i>	S544-5284

Infoprint Manager for AIX and Windows

Title	Order number
<i>IBM Infoprint Color 130 Plus Installation Planning Guide</i>	G544-5771
<i>IBM Infoprint Manager: Reference</i>	S544-5475
<i>IBM Infoprint Manager for AIX: Administrator's Guide</i>	S544-5595

z/OS Version 1 Release 2

Title	Order number
<i>z/OS C/C++ Programming Guide</i>	SC09-4765
<i>z/OS C/C++ Run-Time Library Reference</i>	SA22-7821
<i>z/OS Communications Server: IP and SNA Codes</i>	SC31-8791
<i>z/OS Communications Server: IP Application Programming Interface Guide</i>	SC31-8788
<i>z/OS Communications Server: IP Configuration Guide</i>	SC31-8775
<i>z/OS Communications Server: IP Configuration Reference</i>	SC31-8776
<i>z/OS Communications Server: IP Migration</i>	GC31-8773
<i>z/OS Communications Server: SNA Diagnosis Vol 1, Techniques and Procedures</i>	LY43-0088
<i>z/OS Communications Server: SNA Diagnosis Vol 2, FFST Dumps and the VIT</i>	LY43-0089
<i>z/OS Communications Server: SNA Messages</i>	SC31-8790
<i>z/OS Communications Server: SNA Network Implementation Guide</i>	SC31-8777
<i>z/OS Communications Server: SNA Operation</i>	SC31-8779
<i>z/OS Communications Server: SNA Programming</i>	SC31-8829
<i>z/OS Communications Server: SNA Resource Definition Reference</i>	SC31-8778
<i>z/OS Distributed File Service SMB Administration</i>	SC24-5918
<i>z/OS Information Roadmap</i>	SA22-7500
<i>z/OS ISPF Dialog Developer's Guide and Reference</i>	SC34-4821
<i>z/OS JES2 Commands</i>	SA22-7526
<i>z/OS JES2 Initialization and Tuning Guide</i>	SA22-7532
<i>z/OS JES2 Initialization and Tuning Reference</i>	SA22-7533
<i>z/OS JES3 Commands</i>	SA22-7540
<i>z/OS JES3 Initialization and Tuning Guide</i>	SA22-7549
<i>z/OS JES3 Initialization and Tuning Reference</i>	SA22-7550
<i>z/OS Language Environment Debugging Guide</i>	GA22-7560
<i>z/OS Language Environment Run-Time Messages</i>	SA22-7566
<i>z/OS Language Environment Programming Guide</i>	SA22-7561
<i>z/OS MVS Diagnosis: Tools and Service Aids</i>	GA22-7589
<i>z/OS MVS Initialization and Tuning Guide</i>	SA22-7591
<i>z/OS MVS Initialization and Tuning Reference</i>	SA22-7592
<i>z/OS MVS JCL Reference</i>	SA22-7597
<i>z/OS MVS Product Management</i>	SA22-7603

Title	Order number
<i>z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN</i>	SA22-7609
<i>z/OS MVS Programming: Authorized Assembler Services Reference ENF-IXG</i>	SA22-7610
<i>z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU</i>	SA22-7611
<i>z/OS MVS Programming: Authorized Assembler Services Reference SET-WTO</i>	SA22-7612
<i>z/OS and z/OS.e Planning for Installation</i>	GA22-7504
<i>z/OS Program Directory</i>	GI10-0670
<i>z/OS SDSF Operation and Customization</i>	SA22-7670
<i>z/OS Security Server RACF General User's Guide</i>	SA22-7685
<i>z/OS Security Server RACF Security Administrator's Guide</i>	SA22-7683
<i>z/OS Summary of Message Changes</i>	SA22-7505
<i>z/OS UNIX System Services Command Reference</i>	SA22-7802
<i>z/OS UNIX System Services Messages and Codes</i>	SA22-7807
<i>z/OS UNIX System Services Planning</i>	GA22-7800
<i>z/OS UNIX System Services User's Guide</i>	SA22-7801

CICS

Title	Order number
<i>CICS Customization Guide</i>	SC34-5989
<i>CICS Diagnosis Reference</i>	LY33-6099
<i>CICS Resource Definition Guide</i>	SC34-5990
<i>CICS Supplied Transactions</i>	SC34-5992

IMS/ESA® Version 6

Title	Order number
<i>IMS/ESA Administration Guide: System</i>	SC26-8730
<i>IMS/ESA Administration Guide: Transaction Manager</i>	SC26-8731

3270 and SNA data streams

Title	Order number
<i>IBM 3270 Information Display System Data Stream Programmer's Reference</i>	GA23-0059
<i>IBM 3270 Information Display System 3274 Control Unit Description and Programmer's Reference</i>	GA23-0061
<i>IBM 3270 Information Display System Reference Summary</i>	GX20-1878
<i>IBM 3270 Kanji Data Streams</i>	GA18-2980

I

Title	Order number
<i>IPDS and SCS Technical Reference</i>	S544-5312
<i>Systems Network Architecture: Sessions Between Logical Units</i>	GC20-1868

Index

Special characters

/etc/Printsrv/aopd.conf file 51, 59, 64, 69, 78, 82
/etc/Printsrv/aopdxfd.conf 69
\$HOME/.aopconf file 51, 59, 64, 69, 78, 82
%filter-options option 94

Numerics

3270 data stream
 Character Set attribute 164
 DBCS support 164
 MF order 164
 SA order 164
 SFE order 164
 Shift In control 164
 Shift Out control 164
 WSF order 165
3270 data stream support in NetSpool 16
3270 data streams, attributes 208
3270 data streams, command codes 207
3270 data streams, control codes 207

A

accessibility 211
Acrobat Reader considerations for viewing and printing
 transformed PDF files 38
ADDRESS parameter (JCL) 143
 equivalent job attribute 87
address-text attribute 87
Advanced Function Presentation (AFP) files
 printing or viewing from Windows 178
AFP
 transforming to PCL 28
 transforming to PDF 35
 transforming to PostScript 43
AFP (Advanced Function Presentation) files
 printing or viewing from Windows 178
AFP data
 printing on non-AFP printer 150, 151
AFP files
 printing from Windows 178
AFP Printer Driver
 configuring 177
AFP Printer Driver for Windows, overview 4
AFP printers
 configuring on Windows 177
 JCL parameters used by 144
 submitting jobs from Windows 178
AFP resources, using 144
AFP to PCL transform JCL parameters 130
AFP to PDF transform JCL parameters 130
AFP to PostScript transform JCL parameters 130
AFP Viewer plug-in for Windows, overview 5
afp2pcl transform
 supported objects 31

afp2pcltransform
 environment variables 33
 examples 32
 exit values 34
 files 33
 limitations 32
 operand 30
 options 28
afp2pdf transform
 environment variables 41
 examples 40
 exit values 42
 files 42
 limitations 40
 operand 37
 options 35
 supported objects 39
afp2ps transform
 environment variables 48
 examples 47
 exit values 48
 files 48
 limitations 46
 operand 45
 options 43
 supported objects 46
AIX
 increasing time-out value 187
 printing from 185, 187
 querying jobs and printers from 186
AOP_SAP2AFP_RESOURCES environment
 variable 81, 82
AOPBATCH JCL procedure
 DD names 160
 examples 161
 exit values 162
AOPBATCH program 159
AOPCONF environment variable 33, 41, 48, 50, 59,
 64, 69, 78, 82
AOPTIONS environment variable 59
AOPPATH environment variable 59
AOPPRINT JCL procedure 153
 DD statements 154
 examples 155
 exit values 157
aopwin.exe, downloading 171
APIPPTD1 exit 164
APIPPTD2 exit 164
attribute types, 3270 data streams 208
attributes
 abbreviating 86
 address-text 87
 building-text 88
 carriage-control-type 88
 chars 88
 copies 90
 corresponding to JCL parameters 195
 department-text 90

- attributes (*continued*)
 - document-codepage 90
 - document-format 91
 - document-type 92
 - duplex 92
 - filter-options 93
 - form-definition 94
 - forms 95
 - hold 95
 - holding 95
 - in attributes file 86
 - input-tray 95
 - input-tray-number 96
 - jes-priority 97
 - name-text 97
 - of jobs 85
 - output-bin 98
 - output-bin-number 98
 - overlay-back 99
 - overlay-front 99
 - page-definition 100
 - print-error-reporting 100
 - print-queue-name 101
 - printer-ip-address 101
 - resource-library 102
 - room-text 102
 - shift-out-shift-in 103
 - sysout-dataset-name 103
 - sysout-job-id 104
 - sysout-job-name 104
 - table-reference-characters 105
 - title-text 105
 - valid for different printer types 193
 - validating for printer 193
 - x-image-shift 106
 - x-image-shift-front 107
 - y-image-shift-back 107
 - y-image-shift-front 108
- attributes file 86

B

- barcode.tab file 80, 82
- Beginning of File exit 164
- bin number, output 98
- bin, output 98
- binary data support 164
- binary data support in NetSpool 16
- BM parameter (NetSpool) 167
- books 217
- bottom margin parameter (NetSpool) 167
- bracket (SNA architecture) 166
- broadcasting data 16
- BUILDING parameter (JCL) 143
 - equivalent job attribute 88
- building-text attribute 88

C

- cancel command
 - description 50

- cancel command (*continued*)
 - environment variables 50
 - examples 50
 - exit values 51
 - files 51
 - format 50
 - operand 50
 - portability 51
- cancelling jobs
 - cancel command 50
 - from z/OS UNIX System Services 50
- carriage-control-type attribute 88
- chain (SNA architecture) 166
- chars attribute 88
- CHARS parameter
 - DD JCL statement
 - transmitted to remote system 144
 - OUTPUT JCL statement
 - transmitted to remote system 144
- CHARS parameter (JCL) 132
 - equivalent job attribute 89
 - for shift-out, shift-in process 138
- CICS (Customer Information Control System)
 - printing from 163
- class
 - CLASS parameter (JCL) 119
 - example of specifying in JCL 145
 - specifying in JCL 110
 - SYSOUT parameter (JCL) 129
- CLASS parameter (JCL) 119
- Coax Printer Support feature 16
- code page 90
- code points
 - 3270 data streams 207
 - SCS 197
- coded fonts 88
- Color 130 Plus printer, transform for 77
- color limitations 68, 76, 81
- command codes, 3270 data streams 207
- commands
 - afp2pcl 28
 - afp2pdf 35
 - afp2ps 43
 - cancel 50
 - echo 62
 - enq 185
 - lp 52
 - lpq 186
 - lpr 185
 - lpstat 61
 - man 23
 - pcl2afp 66
 - pdf2afp 70
 - ps2afp 70
 - qstat 186
 - sap2afp 79
 - TCP/IP printing commands 185
 - which command to use 25
- completion message 54, 125
- compression, data 165

- configuration file, Infoprint Server 33, 42, 48, 51, 59, 64, 69, 78, 82
- configuration files, sap2afp transform 80, 82
- control codes, 3270 data streams 207
- copies attribute 90
- COPIES parameter (JCL) 120
 - equivalent job attribute 90
- copies, printing multiple 53, 90, 120
- CRTOUTQ command 189

D

- data compression 165
- data encryption 165
- data formats
 - AFP
 - transforming to PCL 28
 - transforming to PDF 35
 - transforming to PostScript 43
 - PCL
 - transforming to AFP 66
 - supported
 - Print Interface 91
 - VTAM
 - restrictions 164
 - supported 163
- data set, MVS
 - printing
 - lp command 54
- data set, z/OS
 - concept 166
 - end-of-file 166
- data streams
 - AFP
 - transforming to PCL 28
 - transforming to PDF 35
 - transforming to PostScript 43
 - PCL
 - transforming to AFP 66
 - supported
 - Print Interface 91
 - VTAM
 - restrictions 164
 - supported 163
- DATAACK parameter (JCL)
 - equivalent job attribute 100
 - transmitted to remote system 144
- DBCS (double-byte character set) support
 - 3270 data stream 164
 - SCS data stream 164
- DD JCL statement 109
 - CHARS parameter
 - equivalent job attribute 89
 - transmitted to remote system 144
 - COPIES parameter 120
 - equivalent job attribute 90
 - DEST parameter 121
 - DEST=IP parameter 121
 - DSNAME parameter 122
 - DUPLEX parameter 132
 - FCB parameter 123
 - DD JCL statement (*continued*)
 - transmitted to remote system 144
 - OFFSETXB parameter 134
 - OFFSETXF parameter 134
 - OFFSETYB parameter 135
 - OFFSETYF parameter 135
 - OUTBIN parameter 135
 - OVERLAYB parameter 136
 - OVERLAYF parameter 136
 - parameters and equivalent job attributes 195
 - specifying parameters on 118
 - SUBSYS parameter 139
 - SYSOUT parameter) 129
 - UCS parameter 138
 - transmitted to remote system 144
 - validation 193
 - ddnames (data definition names)
 - STDENV 160
 - STDERR 154, 160
 - STDOUT 154, 160
 - SYSIN 154
 - default printer
 - defining 52
 - displaying name and location 63
 - querying 63
 - defcp.tab file 81, 82
 - deferred printing
 - difference between SNA network printers and NetSpool 165
 - definition, printer
 - example of specifying in JCL 144
 - specifying in JCL 109
 - department-text attribute 90
 - DEPT parameter (JCL) 143
 - equivalent job attribute 90
 - description
 - afp2pcl command 28
 - afp2pdf command 35
 - afp2ps command 43
 - cancel command 50
 - lp command 52
 - lpstat command 61
 - pcl2afp command 66
 - pdf2afp command 70
 - ps2afp command 70
 - sap2afp command 79
 - DEST parameter (JCL) 121
 - DEST=IP parameter (JCL) 121
 - equivalent job attribute 101
 - destination
 - example of specifying in JCL 145
 - specifying in JCL 110, 121
 - diagram of system flow 6
 - disability 211
 - displaying job status
 - from z/OS UNIX System Services 61
 - lpstat command 61
 - displaying printer information
 - from z/OS UNIX System Services 61
 - lpstat command 61

- distribution parameters
 - specifying on OUTPUT JCL statement 143
- document-codepage attribute 90
- document-format attribute 91
- document-type attribute 92
- documents, licensed xviii
- DSNAME parameter (JCL) 122
- duplex
 - specifying in JCL 132
- duplex attribute 92
- DUPLEX parameter (JCL) 132
 - equivalent job attribute 92
- duplex printing 92
- dynamic resource library 139

E

- e-mail
 - alias file 112
 - AOPPRINT 153
 - DSNAME parameter considerations 123
 - example 148, 149
 - JCL parameters 110
 - lp command 55
 - RETRYL parameter consideration 128
 - RETRYT parameter considerations 129
 - TITLE parameter consideration 130
 - Windows system 177
- echo command 62
- encryption, data 165
- end-of-bracket 166
- end-of-chain 166
- end-of-file rules
 - default 166
 - end-of-bracket 166
 - end-of-chain 166
 - end-of-session 166
 - string of data 166
 - timer expiration 166
- end-of-session 166
- ENDWTR command 189
- English man pages 23
- English messages 24
- enq command 185, 187
- environment variables
 - afp2pcl command 33
 - afp2pdf command 41
 - afp2ps command 48
 - AOP_SAP2AFP_RESOURCES 82
 - AOPCONF 33, 41, 48, 50, 59, 64, 69, 78, 82
 - AOPTIONS 59
 - AOPPATH 59
 - cancel command 50
 - lp command 59
 - LPDEST 59, 62
 - lpstat command 64
 - MANPATH 23
 - NLSPATH 24, 33, 41, 48, 51, 59, 64, 69, 78, 82
 - pcl2afp command 69
 - pdf2afp command 78
 - PRINTER 59, 62

- environment variables *(continued)*
 - psf2afp command 78
 - sap2afp command 82
- ERRCLASS parameter, AOPPRINT JCL
 - procedure 154
- error messages
 - AOPPRINT JCL procedure
 - class 154
 - sysout name 154
 - English 24
 - Japanese 24
- examples
 - afp2pcl command 32
 - afp2pdf command 40
 - afp2ps command 47
 - AOPBATCH JCL procedure 161
 - AOPBATCH JCL procedure, using transforms 161
 - AOPPRINT JCL procedure 155
 - cancel command 50
 - CRTOUTQ command 189
 - ENDWTR command 189
 - enq command
 - AIX 187
 - JCL parameters 144
 - lp command 55
 - lpr command
 - OS/2 188
 - OS/390 189
 - OS/400 191
 - VM 189
 - z/OS, remote system 189
 - z/VM 189
 - LPR command
 - Windows 179
 - lpstat command 63
 - pcl2afp command 68
 - pdf2afp command 77
 - ps2afp command 77
 - sap2afp command 81
 - STRRTWTR command 189
- exit values
 - afp2pcl command 34
 - afp2pdf command 42
 - afp2ps command 48
 - AOPBATCH JCL procedure 162
 - AOPPRINT JCL procedure 157
 - cancel command 51
 - lp command 59
 - lpstat command 64
 - pcl2afp command 69
 - pdf2afp command 78
 - ps2afp command 78
 - sap2afp command 82

F

- FCB parameter
 - DD JCL statement
 - transmitted to remote system 144
 - OUTPUT JCL statement
 - transmitted to remote system 144

- FCB parameter (JCL) 123
- file-reference document, definition 92
- files
 - /etc/Printsrv/aopd.conf 51, 59, 64, 69, 78, 82
 - \$HOME/.aopconf 51, 59, 64, 69, 78, 82
 - afp2pcl command 33
 - afp2pdf command 42
 - afp2ps command 48
 - barcode.tab 80, 82
 - cancel command 51
 - defcp.tab 81, 82
 - fonts.tab 81, 82
 - image.tab 81, 82
 - lp command 59
 - lpstat command 64
 - pagedef.tab 81, 82
 - pcl2afp command 69
 - pdf2afp command 78
 - printing from Windows 178
 - ps2afp command 78
 - sap2afp command 80, 82
 - xxxx0000.tab 81, 82
- filter-options attribute 93
 - example of specifying LPD compatibility filter options 58
 - example of specifying transform filter options 56
- filter options for AFP to PCL transform 66
- filter options for AFP to PDF transform 35
- filter options for AFP to PostScript transform 43
- filter options for PCL to AFP transform 28
- filter options for PDF to AFP transform 70
- filter options for PostScript to AFP transform 70
- filter options for SAP to AFP transform 79
- filters, passing options to 93
- finding printers 63
- FM (Function Management) header 164
- fonts
 - selection of 132
 - specified in JCL 132
 - specified in page definition 132
 - specifying process mode for 138
- fonts, coded 88
- fonts.tab file 81, 82
- form 95
- form definition 94
 - description 133
 - inline 133
 - selecting 133
 - specifying in JCL 133
- form feed support in a 3270 data stream 208
- form name
 - example of specifying in JCL 145
- FORMS parameter (JCL) 124
 - specifying in JCL 110
- SYSOUT parameter (JCL) 129
- form-definition attribute 94
- format
 - afp2pcl command 28
 - afp2pdf command 35
 - afp2ps command 43
 - cancel command 50

- format (*continued*)
 - lp command 52
 - lpstat command 61
 - pcl2afp command 66
 - pdf2afp command 70
 - ps2afp command 70
 - sap2afp command 79
- formats, data
 - AFP
 - transforming to PCL 28
 - transforming to PDF 35
 - transforming to PostScript 43
 - PCL
 - transforming to AFP 66
 - supported
 - Print Interface 91
 - VTAM
 - restrictions 164
 - supported 163
- FORMDEF parameter (JCL) 133
 - equivalent job attribute 94
 - transmitted to remote system 144
- forms attribute 95
- FORMS parameter (JCL) 124, 133
 - equivalent job attribute 95
- FS45 image type 77
- FS45, limitation in AFP transform 32, 40, 47
- FSSDATA='printer' parameter (JCL) 124
 - example 144
- Function Management (FM) header 164

G

- general printers
 - job attributes valid for 193

H

- hold attribute 95
- holding jobs 95
- horizontal tab parameter (NetSpool) 167
- host name
 - specifying in JCL 121
 - specifying with job attribute 101
- HT parameter (NetSpool) 167

I

- image.tab file 81, 82
- IMS (Information Management System)
 - printing from 163
- Infoprint Port Monitor for Windows
 - description 169
 - downloading to Windows 170
 - installing on Windows 171
 - uninstalling on Windows 180
- Infoprint Port Monitor for Windows, overview 4
- Infoprint Server Transforms
 - AOPBATCH JCL procedure examples 161
 - parameters 130
- Infoprint Server Transforms, overview 12

- Infoprint XML Extender 83
- informational messages
 - AOPPRINT JCL procedure
 - class 154
 - sysout name 154
 - English 24
 - Japanese 24
- inline form definitions 133
- inline page definitions 137
- inline resources
 - fonts 132
 - form definitions 133
 - page definitions 137
- input data streams
 - AFP
 - transforming to PCL 28
 - transforming to PDF 35
 - transforming to PostScript 43
 - PCL
 - transforming to AFP 66
 - supported
 - Print Interface 91
 - VTAM
 - restrictions 164
 - supported 163
- input data streams, types supported 15
- input tray 95
- input-tray attribute 95
- input-tray number attribute 96
- Internet printers
 - defining to Windows 176
- Internet Printing Protocol (IPP), using from Windows 176
- inray
 - specifying in JCL 134
- INTRAY parameter (JCL) 134
 - equivalent job attribute 96
- IOCA FS45, limitation in AFP transform 32, 40, 47
- IP (Internet Protocol) address
 - example of specifying in JCL 145
 - specifying in JCL 110, 121
 - specifying with job attribute 101
- IP PrintWay
 - printing batch jobs 109
- IP PrintWay printers
 - job attributes valid for 193
 - printing batch jobs 109
- IP PrintWay, overview 16
- IPP (Internet Printing Protocol), using from Windows 176

J

- Japanese messages 24
- JCL (job control language)
 - ADDRESS parameter 143
 - equivalent job attribute 87
 - BUILDING parameter 143
 - equivalent job attribute 88
 - CHARS parameter
 - equivalent job attribute 89

- JCL (job control language) *(continued)*
 - CHARS parameter *(continued)*
 - transmitted to remote system 144
 - CLASS parameter 119
 - COPIES parameter 120
 - equivalent job attribute 90
 - DATACK parameter
 - equivalent job attribute 100
 - transmitted to remote system 144
 - DD statement 109
 - DEPT parameter 143
 - equivalent job attribute 90
 - DEST parameter 121
 - DEST=IP parameter 121
 - equivalent job attribute 101
 - DSNAME parameter 122
 - DUPLEX parameter 132
 - equivalent job attribute 92
 - ERRCLASS parameter 154
 - examples 144
 - FCB parameter 123
 - transmitted to remote system 144
 - FORMDEF parameter 133
 - equivalent job attribute 94
 - transmitted to remote system 144
 - FORMS parameter 124
 - equivalent job attribute 95
 - FSSDATA='printer' 124
 - INTRAY parameter 134
 - equivalent job attribute 96
 - NAME parameter 143
 - equivalent job attribute 98
 - NOTIFY parameter 125
 - OFFSETXB parameter 134
 - equivalent job attribute 107
 - OFFSETXF parameter 134
 - equivalent job attribute 107
 - OFFSETYB parameter 135
 - equivalent job attribute 108
 - OFFSETYF parameter 135
 - equivalent job attribute 108
 - OPTIONS parameter 154
 - OUTBIN parameter 135
 - equivalent job attribute 98
 - OUTCLASS parameter 154
 - OUTPUT statement 109
 - OVERLAYB parameter 136
 - equivalent job attribute 99
 - OVERLAYF parameter 136
 - equivalent job attribute 100
 - PAGEDEF parameter 136
 - equivalent job attribute 100
 - transmitted to remote system 144
 - parameters used with IP PrintWay 118
 - PORTNO parameter 125
 - PRINTER parameter 154
 - printing
 - AOPBATCH program 159
 - AOPPRINT procedure 153
 - OUTPUT and DD statements 109
 - to IP PrintWay printers 109

JCL (job control language) *(continued)*

- PRMODE parameter 137, 138
 - equivalent job attribute 103
 - transmitted to remote system 144
- PRTOPTNS parameter 126
- PRTQUEUE parameter 127
 - equivalent job attribute 101
- PRTY parameter
 - equivalent job attribute 97
- RETAINF parameter 127
- RETAINS parameter 128
- RETRYL parameter 128
- RETRYT parameter 129
- ROOM parameter 143
 - equivalent job attribute 102
- SUBSYS parameter 139
- SYSOUT parameter) 129
- TITLE parameter 130, 143
 - equivalent job attribute 106
- transforming data 109
- TRC parameter
 - equivalent job attribute 105
 - transmitted to remote system 144
- UCS parameter 138
 - transmitted to remote system 144
- USERLIB parameter 139
 - equivalent job attribute 102

JCL parameters

- CHARS 132
- USERLIB 139

JCL Parameters

- FORMS 133

JES (Job Entry Subsystem)

- work-selection criteria
 - specifying in JCL 109

jes-priority attribute 97

job attributes

- address-text 87
- building-text 88
- carriage-control-type 88
- chars 88
- copies 90
- department-text 90
- document-codepage 90
- document-format 91
- document-type 92
- duplex 92
- filter-options 93
- form-definition 94
- forms 95
- hold 95
- holding 95
- input-tray 95
- input-tray-number 96
- jes-priority 97
- name-text 97
- output-bin 98
- output-bin-number 98
- overlay-back 99
- overlay-front 99
- page-definition 100

job attributes *(continued)*

- print-error-reporting 100
- print-queue-name 101
- printer-ip-address 101
- resource-library 102
- room-text 102
- shift-out-shift-in 103
- sysout-dataset-name 103
- sysout-job-id 104
- sysout-job-name 104
- table-reference-characters 105
- title-text 105
- valid for different printer types 193
- validating for printer 193
- x-image-shift 106
- x-image-shift-front 107
- y-image-shift-back 107
- y-image-shift-front 108

job ID, Infoprint Server 54, 155

job states 61

jobs

- cancelling
 - cancel command 50
 - from z/OS UNIX System Services 50
- displaying status
 - from z/OS UNIX System Services 61
 - lpstat command 61
- notification when complete
 - lp command 54
 - NOTIFY parameter (JCL) 125
- printing
 - AOPPRINT JCL procedure 153
 - from AIX 187
 - from OS/2 188
 - from OS/390 189
 - from OS/400 189
 - from VM or z/VM 189
 - from Windows 169, 179
 - from z/OS 109, 153
 - from z/OS (remote system) 189
 - from z/OS (VTAM applications) 163
 - from z/OS UNIX System Services 52
 - lp command 52
 - OUTPUT and DD JCL statements 109
 - to IP PrintWay printers 109
- priority 97
- querying
 - from AIX 186
 - from remote systems 186
 - from z/OS UNIX System Services 61
 - lpq command 186
 - lpstat command 61
 - qstat command 186
- validating 193

K

- Kanji AFP Print feature 12
- Kanji print feature 70
- keyboard 211

L

- LAN (local area network) printers
 - job attributes valid for 193
 - not defined by administrator 55
- language
 - changing
 - messages 24
- left margin parameter (NetSpool) 167
- licensed documents xviii
- limitations
 - afp2pcl command 32
 - afp2pdf command 40
 - afp2ps command 46
 - NetSpool 164
 - pcl2afp command 68
 - pdf2afp command 76
 - ps2afp command 76
 - sap2afp command 81
 - SCS data stream 165
 - VTAM data streams 164
- line data format, definition 91
- line-mode data format
 - See line data format, definition
- LM parameter (NetSpool) 167
- local printers
 - defining to Windows 172
- locating printers 63
- LookAt message retrieval tool xix
- lp command
 - description 52
 - environment variables 59
 - examples 55
 - exit values 59
 - files 59
 - format 52
 - operand 54
 - options 52
 - portability 60
- LPD compatibility filter
 - example of specifying options 58
 - filter options for 93
- LPDEST environment variable 59, 62
- lpq command 186
- lpr command
 - AIX example 187
 - OS/2 example 188
 - OS/390 example, remote system 189
 - OS/400 example 191
 - using to print 185
 - VM example 189
 - Windows example 179
 - z/OS example, remote system 189
 - z/VM example 189
- lpstat command
 - description 61
 - environment variables 64
 - examples 63
 - exit values 64
 - files 64
 - format 61
 - operand 63

- lpstat command (*continued*)
 - options 62
 - portability 65
- LU (logical unit)
 - sessions supported 163

M

- man command 23
- man pages
 - English 23
- MANPATH environment variable 23
- margins, specifying
 - NetSpool 167
- maximum presentation line parameter (NetSpool) 167
- maximum presentation position parameter (NetSpool) 167
- medium 95
- message retrieval tool, LookAt xix
- messages
 - AOPPRINT JCL procedure
 - class 154
 - sysout name 154
 - difference between SNA network printers and Infoprint Server 165
 - English 24
 - Japanese 24
 - requesting notification
 - JCL 125
 - lp command 54
- MF (Modify Field) order 164
- migration program, overview 4
- MO:DCA-P data format, definition 91
- Modify Field (MF) order 164
- MPL parameter (NetSpool) 167
- MPP parameter (NetSpool) 167
- multiple transmission of data 146
- MVS data set
 - printing
 - lp command 54

N

- N_UP support 31, 39, 46
- NAME parameter (JCL) 143
 - equivalent job attribute 98
- name-text attribute 97
- NetSpool
 - binary data support 164
 - data compression 165
 - data encryption 165
 - data streams supported 163
 - DBCS support 164
 - differences from SNA network printing 165
 - end-of-file processing 166
 - LU sessions supported 163
 - page formatting for SCS data 166
 - printing with 163
 - restrictions 164
 - transparent data support 164
 - VTAM data streams supported 163

- NetSpool, overview 14
- network printers
 - defining to Windows 175
- NLSPATH environment variable 24, 33, 41, 48, 51, 59, 64, 69, 78, 82
- notification message
 - difference between SNA network printers and NetSpool 165
 - requesting in JCL 125
 - requesting on lp command 54
- NOTIFY parameter (JCL) 125
- Novell NetWare server
 - printing from clients of 192
- number of copies 53, 90

O

- offsetxb
 - specifying in JCL 134
- OFFSETXB parameter (JCL) 134
 - equivalent job attribute 107
- offsetxf
 - specifying in JCL 134
- OFFSETXF parameter (JCL) 134
 - equivalent job attribute 107
- offsetyb
 - specifying in JCL 135
- OFFSETYB parameter (JCL) 135
 - equivalent job attribute 108
- offsetyf
 - specifying in JCL 135
- OFFSETYF parameter (JCL) 135
 - equivalent job attribute 108
- one-sided printing 92
- online help
 - English 23
- operands
 - cancel command 50
 - lp command 54
 - lpstat command 63
 - pdf2afp command 76
 - ps2afp command 76
- options
 - afp2pcl command 28, 30
 - afp2pdf command 35, 37
 - afp2ps command 43, 45
 - lp command 52
 - lpstat command 62
 - pcl2afp command 66, 68
 - pdf2afp command 70
 - ps2afp command 70
 - sap2afp command 79, 80
- options component
 - example of specifying in JCL 146
 - specifying name of in JCL 126
- OPTIONS parameter, AOPPRINT JCL procedure 154
- OS/2
 - printing from 188
- OS/390
 - printing from
 - remote system 189

- OS/400
 - printing from 189
- outbin
 - specifying in JCL 135
- OUTBIN parameter (JCL) 135
 - equivalent job attribute 98
- OUTCLASS parameter, AOPPRINT JCL procedure 154
- output bin 98
- output class
 - example of specifying in JCL 145
 - specifying in JCL 110
- OUTPUT JCL statement 109
 - ADDRESS parameter 143
 - equivalent job attribute 87
 - BUILDING parameter 143
 - equivalent job attribute 88
 - CHARS parameter
 - equivalent job attribute 89
 - transmitted to remote system 144
 - CLASS parameter 119
 - COPIES parameter 120
 - equivalent job attribute 90
 - DATAACK parameter
 - equivalent job attribute 100
 - transmitted to remote system 144
 - DEPT parameter 143
 - equivalent job attribute 90
 - DEST parameter 121
 - DEST=IP parameter 121
 - equivalent job attribute 101
 - DUPLEX parameter 132
 - equivalent job attribute 92
 - FCB parameter 123
 - transmitted to remote system 144
 - FORMDEF parameter 133
 - equivalent job attribute 94
 - transmitted to remote system 144
 - FORMS parameter 124
 - equivalent job attribute 95
 - FSSDATA='printer' 124
 - INTRAY parameter 134
 - equivalent job attribute 96
 - NAME parameter 143
 - equivalent job attribute 98
 - NOTIFY parameter 125
 - OFFSETXB parameter 134
 - equivalent job attribute 107
 - OFFSETXF parameter 134
 - equivalent job attribute 107
 - OFFSETYB parameter 135
 - equivalent job attribute 108
 - OFFSETYF parameter 135
 - equivalent job attribute 108
 - OUTBIN parameter 135
 - equivalent job attribute 98
 - OVERLAYB parameter 136
 - equivalent job attribute 99
 - OVERLAYF parameter 136
 - equivalent job attribute 100
 - PAGEDEF parameter 136

OUTPUT JCL statement (*continued*)

- equivalent job attribute 100
- transmitted to remote system 144
- parameters and equivalent job attributes 195
- PORTNO parameter 125
- PRMODE parameter 137
 - equivalent job attribute 103
 - transmitted to remote system 144
- PRTOPTNS parameter 126
- PRTQUEUE parameter 127
 - equivalent job attribute 101
- PRTY parameter
 - equivalent job attribute 97
- RETAINF parameter 127
- RETAINS parameter 128
- RETRYL parameter 128
- RETRYT parameter 129
- ROOM parameter 143
 - equivalent job attribute 102
- specifying parameters on 118
- TITLE parameter 130, 143
 - equivalent job attribute 106
- TRC parameter 138
 - equivalent job attribute 105
 - transmitted to remote system 144
- UCS parameter 138
 - transmitted to remote system 144
- USERLIB parameter
 - equivalent job attribute 102
- validation 193
- output-bin attribute 98
- output-bin-number attribute 98
- overlay
 - back of page 99
 - front of page 99
- overlay-back attribute 99
- overlay-front attribute 99
- overlayb
 - specifying in JCL 136
- OVERLAYB parameter (JCL) 136
 - equivalent job attribute 99
- overlayf
 - specifying in JCL 136
- OVERLAYF parameter (JCL) 136
 - equivalent job attribute 100
- overview of Infoprint Server components 1
 - AFP Printer Driver for Windows 4
 - AFP Viewer plug-in for Windows 5
 - Infoprint Port Monitor for Windows 4
 - Infoprint Server Transforms 12
 - IP PrintWay 16
 - NetSpool 14
 - Print Interface 5
 - Printer Inventory 3
 - Printer Inventory Manager 3
 - Transform Manager 13
 - Windows client 4

P

- page definition 100
 - description 136
 - inline 137
- page formatting
 - NetSpool 166
- page printer
 - selection 139
- page-definition attribute 100
- PAGEDEF parameter (JCL) 136
 - equivalent job attribute 100
 - transmitted to remote system 144
- pagedef.tab file 81, 82
- parameters
 - AOPPRINT JCL statement 153
 - DD JCL statement 118
 - equivalent job attributes 195
 - Infoprint Server Transforms 130
 - OUTPUT JCL statement 118
- partitioned data set, printing
 - lp command 54
- PCL (Printer Control Language) data format
 - definition 91
 - transforming from AFP 28
 - transforming to AFP 66
- pcl2afp transform
 - description 28, 35, 43, 66
 - environment variables 69
 - examples 68
 - exit values 69
 - files 69
 - format 28, 35, 43, 66
 - limitations 68, 81
 - operand 68
 - options 66
 - usage notes 30
- PDF (Portable Document Format) data format
 - definition 91
 - printing considerations 37
 - transforming from AFP 35
 - transforming to AFP 70
 - viewing considerations 37
- pdf2afp transform
 - description 70
 - environment variables 78
 - examples 77
 - exit values 78
 - files 78
 - format 70
 - limitations 76
 - operand 76
 - options 70
- Port Monitor for Windows
 - description 169
 - downloading to Windows 170
 - installing on Windows 171
- port number
 - specifying in JCL 110
- portability
 - cancel command 51
 - lp command 60

- portability (*continued*)
 - lpstat command 65
- PORTNO parameter (JCL) 125
- POSIX standard, extensions to
 - cancel command 51
 - lp command 60
 - lpstat command 65
- PostScript data format
 - definition 91
 - transforming from AFP or line 43
 - transforming to AFP 70
- Print Interface subsystem
 - comparison with AOPBATCH 114
 - comparison with AOPPRINT 114
 - comparison with resubmit for filtering 114
 - description 113
 - JCL example 151, 152
 - JCL parameters 139
 - limitations 115
 - SUBSYS parameter 139
 - using to transform data 115
- Print Interface, overview 5
- print queue
 - example of specifying in JCL 145
 - specifying in JCL 110, 125, 127, 137
 - specifying with job attribute 101
- print-error-reporting attribute 100
- print-queue-name attribute 101
- printer definition
 - example of specifying in JCL 144
 - specifying in JCL 109
- PRINTER environment variable 59, 62
- Printer Inventory Manager, overview 3
- Printer Inventory, overview 3
- PRINTER parameter, AOPPRINT JCL procedure 154
- Printer Port Monitor compared to other Windows printing protocols 170
- Printer Port Monitor for Windows
 - description 169
 - downloading to Windows 170
 - installing on Windows 171
- printer types
 - job attributes valid for 193
- printer-ip-address attribute 101
- printers
 - attributes 193
 - default 52
 - defining to Windows
 - as Internet printers 176
 - as local printers 172
 - as network printers 175
 - displaying names and locations
 - from z/OS UNIX System Services 61
 - lpstat command 61
 - not defined by administrator 55
 - querying
 - from AIX 186
 - from remote systems 186
 - from z/OS UNIX System Services 61
 - lpq command 186
 - lpstat command 61
- printers (*continued*)
 - querying (*continued*)
 - qstat command 186
 - sharing
 - difference between SNA network printers and NetSpool 165
 - SNA network
 - differences from NetSpool 165
- printers, AFP
 - configuring on Windows 177
 - JCL parameters used by 144
 - submitting jobs from Windows 178
- printing
 - AOPPRINT JCL procedure 153
 - enq command 185
 - from AIX 185, 187
 - from OS/2 188
 - from OS/390 189
 - from OS/400 189
 - from VM 189
 - from Windows 169, 179
 - from z/OS 109, 153, 159
 - from z/OS (remote system) 189
 - from z/OS UNIX System Services 52
 - Japanese PDF 70
 - Japanese PostScript 70
 - lp command 52
 - lpr command 185
 - OUTPUT and DD JCL statements 109
 - PDF, Japanese 70
 - PostScript, Japanese 70
 - remotely
 - Novell NetWare 192
 - TCP/IP 185
 - to IP PrintWay printers 109
 - transformed data 109
- PrintWay, overview 16
- priority 97
- prmode
 - description 137
- PRMODE parameter (JCL) 137
 - equivalent job attribute 103
 - printing from VTAM applications 164
 - transmitted to remote system 144
- process mode 138
- PRTOPTNS parameter (JCL) 126
 - description 126
 - example 146
- PRTQUEUE parameter (JCL) 127
 - description 125, 127
 - equivalent job attribute 101
 - example 145
- PRTY parameter (JCL)
 - equivalent job attribute 97
- ps2afp transform
 - description 70
 - environment variables 78
 - examples 77
 - exit values 78
 - files 78
 - format 70

- ps2afp transform (*continued*)
 - limitations 76
 - operand 76
 - options 70
- PSF for OS/390 printers
 - job attributes valid for 193
- PSF for OS/390, JCL example 148, 149, 152
- PSF for OS/390, relationship to Infoprint Server 2, 4
- PSP bucket xix
- publications 217

Q

- qstat command 186
- querying jobs
 - from AIX 186
 - from remote systems 186
 - from z/OS UNIX System Services 61
- lpq command 186
- lpstat command 61
- qstat command 186
- querying printers
 - from AIX 186
 - from remote systems 186
 - from z/OS UNIX System Services 61
- lpq command 186
- lpstat command 61
- qstat command 186
- queue, print
 - example of specifying in JCL 145
 - specifying in JCL 110, 125, 127, 137
 - specifying with job attribute 101

R

- RATIO keyword in page definition 32
- remote printers 55
- remote printing
 - Novell NetWare 192
 - TCP/IP 185
- remote systems
 - querying jobs and printers from 186
- requesting in JCL 125
- requesting on lp command 54
- resource-library attribute 102
- resources, AFP 144
- restrictions
 - afp2pcl command 32
 - afp2pdf command 40
 - afp2ps command 46
 - NetSpool 164
 - pcl2afp command 68
 - pdf2afp command 76
 - ps2afp command 76
 - sap2afp command 81
 - SCS data stream 165
 - VTAM data streams 164
- resubmit for filtering considerations 110, 122, 123, 126, 127
- resubmit for filtering, used to transform data 117
- RETAINF parameter (JCL) 127

- RETAINF parameter (JCL) (*continued*)
 - description 127
 - example 147
- RETAINS parameter (JCL) 128
- RETAINS parameter (JCL) statement
 - description 128
 - example 147
- retention parameters
 - example of specifying in JCL 147
 - specifying in JCL 127
- retry parameters
 - example of specifying in JCL 147
 - specifying in JCL 128
- RETRYL parameter (JCL) 128
 - description 128
 - example 147
- RETRYT parameter (JCL) 129
 - description 129
 - example 147
- return codes
 - afp2pcl command 34
 - afp2pdf command 42
 - afp2ps command 48
 - AOPPRINT JCL procedure 157
 - cancel command 51
 - lp command 59
 - lpstat command 64
 - pcl2afp command 69
 - pdf2afp command 78
 - ps2afp command 78
 - sap2afp command 82
- right margin parameter (NetSpool) 167
- RM parameter (NetSpool) 167
- ROOM parameter (JCL) 143
 - equivalent job attribute 102
- room-text attribute 102
- RU (request unit)
 - bracket 166
 - chain 166

S

- SA (Set Attribute) order 164
- SAP ABAP (Advanced Business Application Programming) data format
 - definition 91
 - transforming to AFP 79
- SAP OTF (Output Text Format) data format
 - definition 91
 - transforming to AFP 79
- SAP R/3 printing, overview 9, 10
- sap2afp transform
 - customization 80
 - description 79
 - environment variables 82
 - examples 81
 - exit values 82
 - files 80, 82
 - format 79
 - operand 80
 - options 79

- SCS (SNA Character Stream)
 - APIPPTD1 exit 164
 - APIPPTD2 exit 164
 - Beginning of File exit 164
 - DBCS support 164
 - FM header 164
 - restrictions 165
 - Set Attribute control 164
 - SHF command 166
 - Shift In control 164
 - Shift Out control 164
 - SVF command 166
 - transparent data 164
 - Transparent Data Control exit 164
 - TRN (Transparent) control 164
 - SCS data stream support in NetSpool 16
 - selecting
 - fonts 132
 - printer 139
 - sense codes 197
 - sequential data set, printing
 - lp command 54
 - Server Message Block (SMB) printing protocol 169, 171
 - Server Message Block compared to other printing protocols 170
 - sessions, LU
 - supported 163
 - Set Attribute (SA) order 164
 - Set Attribute control 164
 - Set Horizontal Format (SHF) command 166
 - Set Vertical Format (SVF) command 166
 - SFE (Start Field Extended order 164
 - shared network printers
 - defining to Windows 175
 - SHF (Set Horizontal Format) command 166
 - Shift In control
 - 3270 data stream 164
 - line data 103
 - SCS data stream 164
 - Shift Out control
 - 3270 data stream 164
 - line data 103
 - SCS data stream 164
 - shift-out-shift-in attribute 103
 - shift-out, shift-in codes
 - CHARS parameter (JCL) for 138
 - shift-out, shift-in codes (SOSI)
 - PRMODE, (JCL) parameter for 138
 - shortcut keys 211
 - sides to print on 92
 - simple-text data format
 - See text data format, definition
 - SMB (Server Message Block) printing protocol 169, 171
 - SMB compared to other printing protocols 170
 - SNA (Systems Network Architecture)
 - bracket 166
 - chain 166
 - data set boundaries 166
 - end-of-file 166
 - SNA (Systems Network Architecture) *(continued)*
 - network printers
 - differences from NetSpool 165
 - SNA sense codes 197
 - SNMP subagent, overview 19
 - SOSI (shift-out, shift in) codes 138
 - SOSI1 137
 - SOSI2 137
 - SOSI3 137
 - standard input, printing from
 - lp command 54
 - Start Field Extended (SFE) order 164
 - states, job 61, 186
 - STDENV DD name 160
 - STDERR DD name 160
 - STDERR DD statement 154
 - STDOUT DD name 160
 - STDOUT DD statement 154
 - STRRMTWTR command 189
 - SUBSYS parameter (JCL) 139
 - subsystem, Print Interface
 - comparison with AOPBATCH 114
 - comparison with AOPPRINT 114
 - comparison with resubmit for filtering 114
 - description 113
 - JCL example 151, 152
 - JCL parameters 139
 - limitations 115
 - SUBSYS parameter 139
 - using to transform data 115
 - SVF (Set Vertical Format) command 166
 - syntax
 - cancel command 50
 - lp command 52
 - lpstat command 61
 - SYSIN DD statement 154
 - sysout (system output data set)
 - error messages 154, 160
 - informational messages 154, 160
 - SYSOUT parameter (JCL) 129
 - sysout-dataset-name attribute 103
 - sysout-job-id attribute 104
 - sysout-job-name attribute 104
 - system flow diagram 6
- T**
- table reference characters
 - description 138
 - table-reference-characters attribute 105
 - tabs, specifying
 - NetSpool 167
 - TCP/IP printing commands, using 185
 - text data format, definition 91
 - time-out value on AIX, increasing 187
 - TITLE parameter (JCL) 130, 143
 - equivalent job attribute 106
 - title-text attribute 105
 - TM parameter (NetSpool) 167
 - top margin parameter (NetSpool) 167

- transform commands
 - afp2pcl 28
 - afp2pdf 35
 - afp2ps 43
 - pcl2afp 66
 - pdf2afp 70
 - ps2afp 70
 - sap2afp 79
 - xml2afp 83
- Transform Manager, overview 13
- transform XML to AFP 83
- transform, afp2pcl
 - supported objects 31
- transform, afp2pdf
 - supported objects 39
- transform, afp2ps
 - supported objects 46
- transform, passing options to 93
- transforming data 113
- Transparent (TRN) control 164
- Transparent Data Control exit 164
- transparent data support
 - description 164
- transparent data support in NetSpool 16
- tray, input 95, 96
- TRC parameter (JCL) 138
 - equivalent job attribute 105
 - transmitted to remote system 144
- TRN (Transparent) control 164
- tumble duplex printing 92
- two-sided printing 92
- types of LU sessions supported 15

U

- UCS parameter (JCL) 138
 - transmitted to remote system 144
- Unattended port 171, 173, 175
- uninstalling the Infoprint Port Monitor 180
- universal character set
 - description 138
- URI (Uniform Resource Identifier)
 - of printer 176
- URL (Uniform Resource Locator)
 - of printer 176
- userlib
 - description 139
- USERLIB parameter (JCL) 139
 - equivalent job attribute 102

V

- validating print requests 193
- vertical tab parameter (NetSpool) 167
- viewing
 - messages in different languages 24
- VM
 - printing from 189
- VT parameter (NetSpool) 167
- VTAM (Virtual Telecommunications Access Method)
 - data streams supported 163

- VTAM (Virtual Telecommunications Access Method)
 - (continued)
 - LU sessions supported 163
 - printing from 163

W

- Windows
 - defining z/OS printers
 - as Internet printers 176
 - as local printers 172
 - as network printers 175
 - downloading files to 170
 - installing print programs 170
 - printing from 178
 - printing from Windows 169, 179
 - selecting print programs 170
- Windows client, overview 4
- work-selection criteria
 - specifying in JCL 109
- Write Structured Fields (WSF) order 165
- WSF (Write Structured Fields) order 165

X

- X offset
 - back of page 106
 - front of page 107
- x-image-shift-back attribute 106
- x-image-shift-front attribute 107
- XML Extender 83
- XML to AFP transform 83
- xml2afp command 83
- xxxx0000.tab file 81, 82

Y

- Y offset
 - back of page 107
 - front of page 108
- y-image-shift-back attribute 107
- y-image-shift-front attribute 108

Z

- z/OS
 - printing from
 - AOPPRINT JCL procedure 153
 - OUTPUT and DD JCL statements 109
 - remote system 189
 - to IP PrintWay printers 109
 - VTAM applications 163
- z/OS data set
 - concept 166
 - end-of-file 166
- z/OS printers
 - defining to Windows
 - as Internet printers 176
 - as local printers 172
 - as network printers 175

- z/OS UNIX System Services
 - cancelling jobs from 50
 - displaying job status from 61
 - displaying printer information from 61
 - printing from 52
 - querying jobs and printers from 61
- z/VM
 - printing from 189

Readers' comments – we'd like to hear from you

z/OS
Infoprint Server User's Guide

Publication No. S544-5746-04

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Please tell us how we can improve this book:

Thank you for your responses. May we contact you? ☐ Yes ☐ No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Name

Address

Company or Organization

Phone No.



Cut or Fold
Along Line

Fold and Tape

Please do not staple

Fold and Tape



NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation
Information Development
IBM Printing Systems Division
Department H7FE Building 004M
Boulder, CO 80301-9817



Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Program Number: 5694-A01 5697-F51 5655-G52

Printed in U.S.A.

S544-5746-04

