

z/OS



Common Information Model User's Guide

Version 1 Release 13

Note

Before using this information and the product it supports, be sure to read the general information under “Notices” on page 351.

This edition applies to Version 1 Release 13 of z/OS (5694-A01) and to all subsequent releases and modifications until otherwise indicated in new editions.

This edition replaces SC33-7998-07.

© **Copyright IBM Corporation 2005, 2011.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures	vii	Configuring the CIM server's resource authorization model	25
Tables	ix	Enabling the must-stay-clean feature	26
About this publication	xi	Setting up program control	27
Who should use this document	xi	Granting clients and administrators access to the CIM server	28
How to send your comments to IBM	xiii	Switching identity (surrogate)	29
If you have a technical problem	xiii	Configuring the CIM server HTTPS connection using AT-TLS	29
Summary of changes	xv	Example: Configuring AT-TLS for secure communication	30
What's new in z/OS V1R13	xv	Defining the CFZAPPL profile for the APPL class	35
Web Services for Management	xv	Defining an encryption key for PassTicket validation	35
CIM indication delivery retry	xv	Setting up multilevel security (MLS) support	35
Improve the availability of the CIM server by better isolation from faulty providers	xv	Considering Automatic Restart Manager security	36
Indication support for FICON ports	xv	Chapter 7. CIM provider setup and security	37
Enhanced cimcli command	xv	Setting up the CIM server for RMF monitoring	37
New and changed z/OS-specific messages	xvi	Setting up the CIM server for network providers	38
Part 1. Introduction and concepts	1	Setting up the CIM server for Cluster, CoupleDataset, and JES2-JES3Jobs providers	38
Chapter 1. Introduction	3	PARMLIB updates	39
Chapter 2. CIM indication concept	7	RACF setup	39
Indication delivery retry	8	Sysplex couple dataset formatting	39
How indications work	8	Setting up the CIM server for WLM management	40
Chapter 3. z/OS CIM security concept	11	Setting up the CIM server for storage management	41
Part 2. Installation and setup	15	Running providers in a designated user context	42
Chapter 4. Installation	17	Utilizing the provider based authorization model	43
Migration from z/OS 1.11 or z/OS 1.12 to z/OS 1.13	18	Chapter 8. Customization	45
Fallback from z/OS 1.13 to z/OS 1.11 or z/OS 1.12	18	Configuring the ports for the CIM server	45
Chapter 5. Quick guide: CIM server setup and verification	19	Customizing CFZRCUST	46
Step 1: Setting up the security for the CIM server	19	Prerequisites	46
Quick security setup for RACF	19	Option 1: Placing /var/wbem in a separate file system	46
Security setup for a production environment	20	Option 2: Using an existing file system for /var/wbem	48
Step 2: Customizing the file systems and directories	20	System specific directories	48
Step 3: Using default TCP/IP ports 5988 and 5989	21	Customizing the CIM server startup	49
Step 4: Starting the CIM server	21	Customizing the started task procedure CFZCIM	49
Step 5: Customizing the UNIX System Services shell	21	Customizing the UNIX System Services shell	50
Step 6: Running the installation verification program (IVP)	22	Setting the CIM server environment variables	51
Chapter 6. CIM server security setup	23	Selecting a WLM service class for z/OS CIM priority	52
Defining a RACF class and profile for the CIM server	24	Chapter 9. CIM server configuration	53
Defining a CIM server user ID	25	Chapter 10. Setup verification	57
Chapter 7. CIM provider setup and security	37	Part 3. Administration and operation	59

Chapter 11. CIM server administration	61
Starting and stopping the CIM server	61
Running the CIM server as started task	61
Running the CIM server from the UNIX System Services command prompt	62
Running providers in separate address spaces	62
Changing current configuration properties	63
Changing planned configuration properties	63
Tracing	64
Logging	67
Using the syslog daemon for CIM server logging	68
Audit logging with SMF record 86.	69
Backing up the CIM server configuration	70
Automatically restarting the CIM server	70
ARM policy considerations	71
Backing up the CIM server repository	73
Chapter 12. CIM server command-line utilities and console commands	75
cimmo	77
Purpose	77
Syntax	77
Options.	77
Examples	78
cimconfig	79
Purpose	79
Syntax	79
Options.	79
Examples	80
cimprovider	81
Purpose	81
Syntax	81
Options.	81
Limitations	82
Examples	82
cimcli	84
Purpose	84
Syntax	84
Options.	84
cimcli a (associators)	85
cimcli an (associatorNames)	86
cimcli ci (createInstance)	87
cimcli dc (deleteClass)	88
cimcli di (deleteInstance)	89
cimcli dq (deleteQualifier)	90
cimcli ec (enumerateClasses)	91
cimcli ei (enumerateInstances)	92
cimcli eq (enumerateQualifiers)	93
cimcli gc (getClass)	94
cimcli gi (getInstance)	95
cimcli gq (getQualifier)	96
cimcli im (invokeMethod)	97
cimcli mi (modifyInstance)	98
cimcli nc (enumerateClassNames)	99
cimcli ni (enumerateInstanceNames)	100
cimcli ns (enumerateNamespaces)	101
cimcli r (references)	102
cimcli rn (referenceNames)	103
cimcli sp (setProperty)	104
cimcli ti (testInstance)	105

cimcli xq (execQuery)	106
cimcli <i>Options</i>	107
cimcli <i>Instance name</i>	109
cimsub	110
Purpose	110
Syntax.	110
Options	111
Examples.	112
MODIFY console command.	113
Syntax.	113
Options	113
Examples.	113

Part 4. Provider reference 115

Chapter 13. Profiles	117
SMI-S profiles	117
Host Discovered Resources profile	117
SB Multipath Management profile	118
Storage HBA profile	119

Chapter 14. z/OS Management Instrumentation for CIM	121
Supported CIM operations	125
OS management Base classes	126
CIM_ComputerSystem	127
CIM_OperatingSystem	127
CIM_OSProcess	127
CIM_Process	128
CIM_RunningOS	128
IBMzOS_ComputerSystem	129
IBMzOS_OperatingSystem	131
IBMzOS_OSProcess	133
IBMzOS_Process	134
IBMzOS_RunningOS	136
IBMzOS_UnixProcess.	137
OS management BaseBoard classes	138
IBM_BaseBoard.	139
IBMzOS_BaseBoard	140
Association CIM_ComputerSystemPackage	141
Association IBMzOS_CSBaseBoard	141
OS management Processor classes	142
CIM_Processor	143
Association CIM_SystemDevice	143
IBMzOS_Processor	144
OS management Logical Disk classes	146
CIM_LogicalDisk	147
IBMzOS_LogicalDisk	148
OS management File System classes	150
CIM_LocalFileSystem.	151
CIM_RemoteFileSystem	151
Association CIM_HostedFileSystem	151
IBMzOS_UnixLocalFileSystem.	152
IBMzOS_NFS	153
OS management Network classes.	154
CIM_EthernetPort	156
CIM_IPProtocolEndpoint	156
CIM_PortImplementsEndpoint	156
Association CIM_SystemDevice	156
IBMzOS_EthernetPort	157

IBMzOS_IPProtocolEndpoint	158
OS management Job classes	160
IBMzOS_JES2Job	161
IBMzOS_JES3Job	171
IBMzOS_JES2SysoutDataset	180
IBMzOS_JES3SysoutDataset	183
IBMzOS_Job	184
IBMzOS_JobsManagementSettings	185
IBMzOS_Subsystem	186
IBMzOS_SysoutDataset	188
Association IBMzOS_SubsystemJES2Jobs	189
Association IBMzOS_SubsystemJES3Jobs	189
Association IBMzOS_UsesJES2SysoutDatasets	189
Association IBMzOS_UsesJES3SysoutDatasets	189
OS management Cluster classes	191
IBMzOS_CFRMCoupleDataset	192
IBMzOS_CFRMPolicy	194
IBMzOS_CFStructure	196
IBMzOS_CFStructureConnector	206
IBMzOS_CoupleDataset	209
IBMzOS_CouplingFacility	213
IBMzOS_CouplingFunction	217
IBMzOS_SFMAAttributes	220
IBMzOS_Sysplex	221
IBMzOS_SysplexCoupleDataset	224
IBMzOS_SysplexNode	225
Association IBMzOS_CFStrDependsOn	228
Association IBMzOS_CollectionOfCFs	228
Association IBMzOS_CollectionOfSysplexNodes	229
Association IBMzOS_HostedCFStructure	229
Association IBMzOS_HostedCFStrConnector	230
Association IBMzOS_UsesCFs	230
Association IBMzOS_UsesCFRMCoupleDatasets	231
Association IBMzOS_UsesCFRMPolicies	231
Association IBMzOS_UsesCouplingFunctions	231
Association	
IBMzOS_UsesSysplexCoupleDatasets	231
Storage management classes	233
CIM_FCPort	233
CIM_FCPortStatistics	233
CIM_PortController	233
CIM_Product	233
CIM_ProtocolEndpoint	233
CIM_SoftwareIdentity	233
CIM_StorageExtent	233
Association CIM_ControlledBy	234
Association CIM_DeviceSAPIImplementation	234
Association CIM_ElementSoftwareIdentity	234
Association CIM_ElementStatisticalData	234
Association CIM_HostedAccessPoint	234
Association CIM_InitiatorTargetLogicalUnitPath	234
Association CIM_InstalledSoftwareIdentity	234
Association CIM_ProductElementComponent	235
Association CIM_SystemDevice	235
IBMzOS_FCPort	236
IBMzOS_FCPortStatistics	239
IBMzOS_PortController	241
IBMzOS_Product	243
IBMzOS_SBPProtocolEndpoint	244
IBMzOS_SoftwareIdentity	246
Association IBMzOS_ControlledBy	249

Association IBMzOS_CSFCPort	250
Association IBMzOS_CSFCPortController	251
Association IBMzOS_ElementSoftwareIdentity	252
Association IBMzOS_FCPortStatisticalData	253
Association IBMzOS_InstalledSoftwareIdentity	254
Association	
IBMzOS_ProductElementComponent	255
Association	
IBMzOS_SBDeviceSAPIImplementation	256
Association IBMzOS_SBHostedAccessPoint	257
Association	
IBMzOS_SBInitiatorTargetLogicalUnitPath	258

Chapter 15. WLM classes 261

IBMzOS_WLM	262
Association IBMzOS_WLMOS	267

Part 5. Developer's guide 269

Chapter 16. CMPI provider development for z/OS 271

Obtaining the required header files	272
Following general aspects of developing a provider	273
Preparing provider initialization and function signatures	274
Instance provider functions	274
Method provider functions	275
Association provider functions	275
Indication provider functions	275
Planning provider security	275
Converting data to ASCII, EBCDIC and UTF-8	276
Provider installation	276
Installing providers and dependent load modules	277
Customizing the CIM server environment for third-party providers	277
Registering a provider with the CIM server	277
PG_Provider	280
PG_ProviderModule	281
PG_ProviderCapabilities	283
Using the out-of-process support for providers	285
Samples	285

Chapter 17. CIM indications 287

CIM indication class hierarchy	288
CIM_ProcessIndication	288
CIM_InstIndication (Lifecycle Event)	289
CIM_InstModification	289
CIM subscription mechanism	289
CIM_IndicationFilter	290
CIM_ListenerDestinationCIMXML	290
CIM_IndicationSubscription	291

Part 6. Messages 293

Chapter 18. z/OS specific messages 295

CEZ-prefix messages	295
CFZ-prefix messages	300

Part 7. Appendixes	321	 Related links.	343
 Appendix A. Troubleshooting	323	Legend for graphics showing class structures	345
Garbage on the screen	323	How to read syntax diagrams	347
Typical error scenarios	323	Accessibility.	349
Appendix B. Step-by-step explanation of the CFZSEC job	327	Using assistive technologies	349
 Step BASICSUP	327	Keyboard navigation of the user interface	349
Step CRUSR.	328	z/OS information	349
Step CRWBEM.	329	Notices	351
Step PEUSR.	330	Programming Interface Information	352
Step PEAPPL	331	Trademarks	352
Step SETARM	331	Terms and conditions for downloading and printing publications	353
Step ENSTC.	332	Policy for unsupported hardware.	353
Step PECEA.	333	Index	355
Step ENCLCDS.	334		
Step ENSMIS	335		
Step ENTCPIP	336		
Step ENWLM	336		
Step ENRMF	337		
 Appendix C. CEA reason codes	339		

Figures

1.	Sample network environment managed with CIM management applications	3		11.	OS management File System classes	150	
2.	Exemplary components of the CIM server in a z/OS environment	5		12.	OS management Network classes	155	
3.	CIM indication flow and processing.	8		13.	WLM classes.	261	
	4.	Security components	12		14.	WLM indications	262
5.	Host Discovered Resources Instance Diagram	118		15.	CMPI provider interfaces	271	
6.	HBA instance diagram	119		16.	OpenPegasus CVS Repository	273	
	7.	CIM Base classes extended by z/OS-specific classes (1).	126		17.	CIM classes from the provider registration schema	278
	8.	OS management BaseBoard Class.	138		18.	z/OS CIM indication hierarchy	288
	9.	OS management Processor classes.	142		19.	Indication subscription class diagram	289
	10.	CIM Base classes extended by z/OS-specific classes (2).	147		20.	Indication Handler.	291

Tables

1.	Default SMP/E installation directories for	5.	CIM server configuration properties	53
	z/OS CIM	6.	Log and syslog levels	68
	2. Access types required for CIM operations	7.	UCB control block information.	149
	3. Sample sysplex couple dataset formatting JCL	8.	Jobs providers' reason codes	339
	4. Installation directories for z/OS CIM	9.	UML syntax	345
				48

About this publication

This document describes the implementation of the Common Information Model (CIM) and Web Based Enterprise Management (WBEM) standards for z/OS. It explains how to set up and use the CIM server and CIM resource instrumentation provided together with the z/OS operating system. CIM is a standard data model for describing and accessing systems management data in heterogeneous environments. It allows system administrators and vendors to write applications that monitor and manage system resources in a network with different operating systems and hardware.

The focus of this document is on the z/OS-specific implementation of CIM. For more detailed information about the CIM and WBEM standards please review the information provided by the Distributed Management Task Force (DMTF), which is found in the internet on the *DMTF website*.

This document describes how to set up security using Resource Access Control Facility (RACF®) as security product. However, you can use any other suitable security product for this purpose.

Explicit link addresses are listed in “Related links” on page 343.

Who should use this document

This document is intended for all users of the z/OS Common Information Model (CIM). It covers all z/OS specific aspects of CIM including installation, configuration and setup, application development, and problem diagnosis.

How to send your comments to IBM

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Use one of the following methods to send us your comments:

1. Send an e-mail to s390id@de.ibm.com
2. Visit the Contact z/OS website at <http://www.ibm.com/systems/z/os/zos/webqs.html>
3. Mail the comments to the following address:
IBM Deutschland Research & Development GmbH
Department 3248
Schönaicher Str. 220
D-71032 Böblingen
Federal Republic of Germany
4. Fax the comments to us as follows:
From Germany: 07031-16-3456
From all other countries: +(49)+7031-16-3456

Include the following information:

- Your name and address
- Your e-mail address
- Your telephone or fax number
- The publication title and order number:
Common Information Model User's Guide
SC33-7998-08
- The topic and page number related to your comment
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

If you have a technical problem

Do not use the feedback methods listed above. Instead, do one of the following:

- Contact your IBM service representative
- Call IBM technical support
- Visit the IBM zSeries support website at <http://www.ibm.com/systems/z/support/>

Summary of changes

This document contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations in the present release are indicated by a vertical line to the left of the change.

The following sections list the changes that have been made to CIM with various operating system releases.

What's new in z/OS V1R13

Web Services for Management

The CIM server now implements the WS-Transfer and WS-Enumeration operations of the Web Services for Management (WS-Management) standards. The behavior of the CIM server processing WS-Management requests is guided by these standards:

- DMTF DSP0226: Web Services for Management (WS-Management) Specification
- DMTF DSP0227: WS-Management CIM Binding Specification
- DMTF DSP0230: WS-CIM Mapping Specification

Not all mandatory requirements in these specifications are met in this version of the CIM server.

For this, the new trace component `WsmServer` has been introduced.

CIM indication delivery retry

With z/OS 1.13, the implementation of the DMTF Indications Profile DSP1054 1.1 introduces sequence identifiers to deliver indications more reliably.

Improve the availability of the CIM server by better isolation from faulty providers

The new configuration property *maxFailedProviderModuleRestarts* determines the number of times a failed provider module with indications enabled is restarted automatically before it is disabled.

Indication support for FICON ports

IBMzOS_PortController now supports indication subscriptions to the creation and deletion of port controllers. IBMzOS_SBInitiatorTargetLogicalUnitPath now supports the indication subscriptions to the creation, modification, and deletion of channel path connections between disk devices and z/OS channel ports.

Enhanced cimcli command

The `cimcli` command has been modified: The new function `setProperty` allows to set a single property on a named instance.

New and changed z/OS-specific messages

The following z/OS-specific messages have been added or changed:

CEZ03000E	CEZ03001E	CEZ03002W	CEZ03003W	CEZ03004I	CEZ03005I
CEZ03006E	CEZ03007E	CEZ03008W	CEZ03009W	CEZ05010E	CEZ05011E
CEZ03012E	CFZ00409E	CFZ07801E	CFZ08001W	CFZ10033E	CFZ10206W
CFZ10215W	CFZ10405W	CFZ12530E	CFZ12535W		

Part 1. Introduction and concepts

Chapter 1. Introduction

The Common Information Model (CIM) is a standard data model developed by a consortium of major hardware and software vendors (including IBM®) called the Distributed Management Task Force (DMTF) as part of the Web Based Enterprise Management (WBEM) initiative. WBEM includes a set of standards and technologies that provide management solutions for a distributed network environment. Interoperability is a major focus of WBEM, and using WBEM technologies can help you develop a single set of management applications for a diverse set of resources and systems.

Figure 1 shows a sample environment in which management applications can run that use the DMTF CIM standard data model.




Figure 1. Sample network environment managed with CIM management applications

CIM is a major component of the WBEM initiative, providing a model for describing and accessing data across an enterprise. CIM consists of both a specification and a schema. The specification defines the details for integration with other management models, while the schema provides the actual model descriptions.

CIM supports the concept of indications as described in Chapter 2, "CIM indication concept," on page 7.

With support for the CIM server on systems running z/OS, users have the ability to access z/OS resources through an extendible industry standard model. This document contains information about how to use the CIM server for z/OS for this

purpose.

CIM for z/OS includes:

CIM server

The open source implementation of the CIM server manages the communication between clients and providers. The CIM server also provides several management functions, including security, and a set of commands that provide configuration and management functions to administrators.

The CIM server implementation on z/OS is based on the OpenPegasus CIM server from The Open Group. See the OpenPegasus website for more information.

CIM operations over HTTP

The "CIM over HTTP" protocol is an implementation of the standardized formats for communication between clients and the CIM server *Representation of CIM in XML (DSP0201)* and *CIM Operations over HTTP (DSP0200)*. The CIM server for z/OS supports most of the CIM operations defined in the CIM Operations over HTTP specification by the DMTF.

For more information about these standards, see the WBEM website.

Web Services for Management

With z/OS 1.13, the CIM server for z/OS supports the WS-Transfer and WS-Enumeration operations defined in the WS-CIM Mapping specification. Web Services for Management (DSP0226) is a general SOAP-based protocol for managing systems. The WS-CIM Mapping specification (DSP0230) describes how to use the Web Services for Management (WS-Management) protocol to communicate with resources modeled with CIM and exposed through the XML schema mapping described by the WS-Management CIM Binding Specification (DSP0227).

DMTF CIM Schema

A CIM Schema defines an information model for representing systems management functions. For z/OS 1.13, CIM Schema version 2.25 is supported by the CIM server.

Instrumentation for server resources

Instrumentation for server resources on the system are called **providers**. The providers, which are based on a subset of the standardized CIM classes, gather data on a system. CIM clients can work with this data by accessing the providers through the CIM server. For more information about what is supported in z/OS, refer to Chapter 14, "z/OS Management Instrumentation for CIM," on page 121.

CIM client for Java

z/OS CIM includes the CIM client for Java library from the SBLIM project. With z/OS 1.13, version 2.1 of the CIM client for Java is included. The CIM client for Java is a programming API that enables z/OS applications written in Java for local and remote access of CIM instrumentation through the CIM over HTTP access protocol. It consists of a Java library and associated online Java documentation.

Note: Version 1 of the CIM client for Java (SBLIM CIM client) will be removed in a future release of z/OS.

Figure 2 illustrates how the CIM server works in the z/OS environment: A CIM client application requests the CIM server to return information about z/OS resources, in this case about basic operating system (OS) data as well as monitoring metrics, in this example RMF™ metrics. The CIM server invokes the according CIM providers which retrieve the requested data associated to z/OS system resources. The z/OS RMF monitoring provider invokes the RMF Distributed Data Server (DDS) which in turn collects RMF Monitor III performance data. The CIM server consolidates the data from the providers and returns them back to the calling client through the CIM over HTTP protocol.

Figure 2 shows two types of CIM providers: RMF monitoring providers that use the RMF DDS to access the z/OS system, and z/OS operating system management providers that access the z/OS system data directly.




Figure 2. Exemplary components of the CIM server in a z/OS environment

Important Note:

Each IBM eServer™ operating system is supporting a specific open source implementation of a CIM server. The "eServer Common Information Model" document contains overall information about how to use CIM for systems management on IBM eServers. Users of CIM for z/OS need to know this information. The present z/OS Common Information Model User's Guide contains the z/OS-specific supplements and deviations from the common eServer CIM and from OpenPegasus.

Chapter 2. CIM indication concept

Copyright attribution:

The introduction to CIM indications provided in this section is based on the information in the CIM Event Model White Paper, DSP0107, Document Version 2.1 June 10, 2003, provided by the Distributed Management Task Force (DMTF).

In CIM terminology, an indication is the representation of the occurrence of an event. For example, an event can be the unexpected termination of a program, or the modification of a property value of a CIM instance. There is not necessarily a one-to-one correspondence between events and indications. In particular, multiple indications can be generated for the same underlying event if multiple CIM client applications had subscribed for the event. An event can also occur without causing a related indication to be raised, for example if no subscription was made for the event.

z/OS supports additional indications for the CIM infrastructure. As an example, the Storage Management CIM providers can generate indications for the state change of channel paths, this way enabling CIM clients to support event-based monitoring to avoid polling the CIM server. A CIM client can subscribe for conditions, for example when a channel path goes offline. While the subscription is active, an according CIM indication provider monitors the resource(s) and notifies the CIM client whenever the condition becomes true.

The CIM indication support comprises the following steps:

- Defining an indication filter condition: This describes the event that you might want to be notified about, that is, when to send an indication
- Defining an indication listener: This describes how and where to send an indication
- Activating the subscription by associating a filter with a listener
- Consuming the indication once it is raised: The indication is sent to the indication listener, which decides how to react to the event

The CIM Event Model defines the CIM classes used for indication support. It defines the CIM indication class hierarchy that is used to model various types of events, and the CIM subscription mechanism.

Further readings:

- CIM Event Model White Paper, DSP0107, Document Version 2.1 June 10,2003, provided by the Distributed Management Task Force (DMTF), describes the CIM Event Model.
- Specification for CIM Operations over HTTP describes how the CIM server transmits CIM indications to the CIM listener.
- DMTF Indications Profile DSP1054 1.1 describes the behavior of CIM indication delivery.
- Chapter 17, “CIM indications,” on page 287 describes CIM indication classes and the CIM subscription mechanism.

Indication delivery retry

To improve the reliability of indication delivery, DMTF Indications Profile DSP1054 1.1 introduces *sequence identifiers*. Sequence identifiers flag the order of deliveries. This makes indication delivery more reliable, because the CIM server can retry unsuccessful deliveries, and a CIM listener can detect lost and duplicate deliveries and reorder indications arriving out of order.

Indication delivery is based on a *publish/subscribe event paradigm*, where a CIM server delivers indications to subscribed WBEM listeners.

If the attempt of a WBEM server to deliver an indication to a WBEM listener fails, the service retries the delivery. For this, the number of delivery retry attempts and the minimum delivery retry interval are specified (with the *DeliveryRetryAttempts* and *DeliveryRetryInterval* properties of the appropriate CIM_IndicationService instance associated with the CIM_IndicationFilter or CIM_FilterCollection instance). Each sequence identifier has a *lifetime*, which is the number of delivery retry attempts multiplied by the minimum delivery retry interval multiplied by 10.

The indication is not delivered to the listener, if the number of retry attempts or the lifetime of the sequence identifier is exceeded.

For more information, see DMTF Indications Profile DSP1054 1.1.

How indications work

Indications are generated and processed as shown in Figure 3 and described in the subsequent list:




Figure 3. CIM indication flow and processing

1. Indication providers are registered:

An indication provider is a CIM provider that recognizes when a particular type of event occurs on the managed system. The indication provider turns that event into a type of CIM_Indication and passes it to the CIM server.

An indication provider is registered with the CIM server just as any other provider is registered using PG_ProviderCapabilities as described in "Registering a provider with the CIM server" on page 277.

2. The CIM client creates the three CIM instances mentioned above:

For this, the CIM client uses the *createInstance* CIM operation. The instances must be created in the root/PG_InterOp namespace of the CIM server.

a. To request the notification of a specific event, a CIM client defines an indication filter condition:

The CIM client issues CIM operation requests to the CIM server to create an instance of the CIM_IndicationFilter class.

The CIM_IndicationFilter instance defines the event with a query string in a query language like CIM Query Language (CQL) or WBEM query language (WQL).

For details on CQL, see the CIM Query Language Specification.

b. To specify how to handle and where to send an indication, the CIM client defines an indication listener:

The CIM client issues CIM operation requests to the CIM server to create an instance of the CIM_ListenerDestination class.

A CIM_ListenerDestination is an abstract superclass that specifies how to handle and where to send the indication. It may define a destination and protocol for delivering indications, or a process to be invoked. z/OS supports the subclass CIM_ListenerDestinationCIMXML as a vehicle to describe the destination URL for indications, which can receive indications in CIMXML format.

c. The CIM client activates the subscription:

The CIM client issues CIM operation requests to the CIM server to create an instance of the CIM_IndicationSubscription class.

A CIM_IndicationSubscription is an association between a CIM_IndicationFilter and a CIM_ListenerDestination (see Figure 19 on page 289).

3. When an event occurs on the managed system, it is detected by the CIM indication provider:

The CIM indication provider turns that event into a specific indication. At this stage, the indication is a local representation of an instance of a subclass of class CIM_Indication. The indication provider delivers that indication to the CIM server for further processing and delivery.

Typically the indication is an instance of a subclass of class CIM_ProcessIndication or class CIM_InstIndication.

4. The CIM server delivers the indications to the CIM listeners:

a. The CIM server filters the indications:

The indications delivered by the indication provider are filtered according to the filter conditions of the active subscriptions.

b. The CIM server generates a CIM export message to transmit the CIM_Indication instance to the CIM listener URL according to the matching filter conditions in the format and protocol specified in the CIM_ListenerDestination instance.

5. The CIM listener receives the CIM_Indication instance:

The CIM listener or CIM server coordinates the distribution of the indication to one or more registered indication consumers and sends CIM export responses.

6. The CIM_Indication is delivered to one or more indication consumers.

Chapter 3. z/OS CIM security concept

Although the CIM server on z/OS is based on the open source implementation, the security design has been considerably extended and adapted to meet the z/OS security strengths.

The CIM server security consists of two major areas: Protection of resources on the managed system through *authentication* and *authorization*, and protection of communicated information through *network security*.

The AT-TLS feature of z/OS is used to encrypt data using SSL for data security on the network. It is recommended to utilize this support.

To protect resources on the managed system from unauthorized access, first of all users have to be authenticated to ensure the CIM server is really communicating with an identified entity (user). Users can be authenticated by either a user identity (ID) and a password, a user identity and a PassTicket, or a user certificate. In all cases after successful authentication the user who wants to access the system is well known and now authorization checks are performed against that specific user identity.

The CIM server performs three types of authorization checks:

1. For each user, the CIM server checks the authority to access CIM. To get general access to CIM, a user needs at least READ access to profile CIMSERV in System Authorization Facility (SAF) class WBEM.
2. The access to the provider is checked. Access to a provider can be explicitly restricted by defining a provider-specific profile in SAF class WBEM and registering the provider with that security profile. This access restriction is optional and depends on whether a provider was registered with a security profile or not.
3. The last checks of authorization are performed based on the z/OS system resources a user tries to access, what effectively means that users can only access the resources for which they were entitled before.




Figure 4. Security components

Figure 4 shows the CIM server runtime environment security:

Network security

AT-TLS provides network security. It is recommended to utilize this feature.

Authentication

Authentication is always enabled for the CIM server. The CIM server checks whether the requestor is entitled to use the CIM server. A requestor authenticates with a user ID and a password, with a user ID and a PassTicket, or with a user certificate.

Authorization

CIM authorization (RACF class WBEM)

The CIM server controls whether the user ID is authorized to access the CIM server using the RACF class WBEM. The profile CIMSERV restricts access to the CIM server.

Provider based authorization

Optionally, a provider can be registered with a specific security profile. In this case, the user ID has to be authorized before it can invoke the provider. A provider-specific profile in RACF class WBEM restricts the access to the provider.

These checks are strongly recommended for providers which use a designated user ID.

z/OS[®] resource authorization

The z/OS system resource access authorization is verified against the requesting user ID.

For authorization purposes to specific z/OS system resources, the CIM server processes requests either under the user ID which has generated the request or under a designated user ID which was registered for the provider. To do this, the CIM server uses thread-level security, which is provided by the UNIX System Services.

For that reason certain providers require additional authorization to extra security profiles.

Additionally, the CIM server is enabled for the *Enhanced Security model*. Under the Enhanced Security model, the CIM server does not load any dynamic load library that is not program controlled, in particular it does not load any such provider dynamic load library.

Part 2. Installation and setup

Chapter 4. Installation

This chapter describes how to install the CIM server, how to migrate the CIM server to the current release, and how to fall back to a previous CIM server version.

- **Use SMP/E to install z/OS CIM for the first time or to migrate z/OS CIM as a replacement of a previous z/OS CIM version.**

For details on installing a product using SMP/E, see *z/OS Program Directory*.

After successful installation, the components of z/OS CIM are located in the following hierarchical file system directory.

Table 1. Default SMP/E installation directories for z/OS CIM

Directory	Description
/usr/lpp/wbem	Base hierarchical file system directory
/usr/lpp/wbem/bin	CIM server executables
/usr/lpp/wbem/lib	CIM server libraries
/usr/lpp/wbem/install	Sample profile
/usr/lpp/wbem/provider	CIM provider libraries provided with z/OS
/usr/lpp/provider/schemas	IBM z/OS instrumentation MOF files
/usr/lpp/wbem/msg	CIM message files for NLS
/usr/lpp/wbem/schemas	DMTF CIM schema files (MOF)
/usr/lpp/wbem/repository	CIM schema master repository
/usr/lpp/wbem/jclient	CIM client for Java
/usr/lpp/wbem/IBM	SMP/E target library path

The modules CFZENF09, CFZENF27, and CFZENF33 are located in system image SYS1.LPALIB. These modules are needed by the Common Event Adapter (CEA) for the life cycle indications defined for the storage management instrumentation.

If you migrate to z/OS 1.13, the new master repository is located in */usr/lpp/wbem/repository*. Previous versions of the repository are backed up as */var/wbem/repository/repository_old_<timestamp>*, where *<timestamp>* is the current time.

- **If you migrate the CIM server to a new z/OS release, it is recommended that you replace the environment variable file *cimserver.env* located in */etc/wbem* with the new sample installed in directory:**

/usr/lpp/wbem

If you do not intend to replace the environment variable file *cimserver.env* with the new sample, make sure that the following directories are included in the LIBPATH defined in *cimserver.env*:

/usr/lpp/wbem/lib:/usr/lpp/wbem/provider:/usr/lib

Migration from z/OS 1.11 or z/OS 1.12 to z/OS 1.13

You can install z/OS 1.13 CIM as described above as a replacement of a previous z/OS CIM version without affecting any external programs interfacing with the CIM server, such as management applications.

During startup, the z/OS 1.13 CIM server will automatically correct eventually missing file tags in its repository. In addition, it will detect if an existing repository is up to date.

If back-level, the CIM server will automatically upgrade the repository in */var/wbem* following these steps:

1. The CIM server backs up the current repository into
repository_old_<timestamp>
where *<timestamp>* is the current time.
2. The CIM server copies the master repository from */usr/lpp/wbem/repository* to */var/wbem/repository*.
3. The CIM server migrates the previous repository content to the current repository.

If the CIM server does not find a repository in */var/wbem* at startup, it automatically creates a default repository from the master repository that is shipped under */usr/lpp/wbem*. To recover a damaged repository, you can create a new repository by removing the damaged repository from */var/wbem*. Then the CIM server creates a new copy at the next startup. Please note that all your custom changes for the repository, for example additional provider registrations, will be lost in this case and have to be done again.

The CIM server also checks for syntactical errors in the *cimserver.env* file located in directory */etc/wbem/*. Errors recognized by the CIM server are automatically corrected. The corrected version of *cimserver.env* replaces the old one, but the startup fails. Restart the CIM server.

Fallback from z/OS 1.13 to z/OS 1.11 or z/OS 1.12

The CIM server does not automatically support fallbacks to a previous version. To do so, you must recover the necessary files from repository backups.

To fall back to a previous z/OS CIM server version,

- ___ 1. Stop the CIM server
- ___ 2. Delete */var/wbem/repository*
- ___ 3. Delete */var/wbem/repository_status*
- ___ 4. Copy */var/wbem/repository_old_<timestamp>* to */usr/lpp/wbem/repository*,
where *<timestamp>* is the time when you migrated from the former to the later release

If this file is no longer available and you do not have your own backup, you can find the originally delivered version in the master repository located in */var/wbem/repository*, but all your changes, such as special provider registrations, will be lost.

- ___ 5. Restart the CIM server

Chapter 5. Quick guide: CIM server setup and verification

This chapter describes the necessary setup steps of the CIM server on a z/OS system. It can be used for a quick setup - to configure CIM without the need to understand the specifics of the CIM server's features and fine-grained authorization model - or as a guide through the setup steps from security setup to customization and finally the setup verification.

To set up the CIM server for the first time, perform the following steps which are described in more detail in the chapters below:

- Step 1. Set up the security for the CIM server (once per security domain/sysplex)
 - For a quick setup, use job CFZSEC from the installation SAMPLIB
- Step 2. Customize the file systems and directories used by the CIM server (once per z/OS system for which you want to configure CIM)
 - Use job CFZRCUST from the installation SAMPLIB
- Step 3. Use the default TCP/IP ports 5988 and 5989
- Step 4. Start the CIM server (once per z/OS system)
 - Copy the CFZCIM started task procedure from the installation PROCLIB
 - START CFZCIM
- Step 5. Customize the UNIX System Services shell
 - Add the content of /usr/lpp/wbem/install/profile.add to /etc/profile or to the user specific profiles residing in the user home path.
- Step 6. Run the installation verification program (IVP) (once per CIM server)
 - Use job CFZIVP from the installation SAMPLIB

Step 1: Setting up the security for the CIM server

The security setup for the CIM server is done once per security domain and works for all systems that share this security domain, for example all systems that use the same shared RACF database.

Quick security setup for RACF

If you are using RACF as your security product, the quickest way to set up CIM server security is using the job CFZSEC provided in the installation SAMPLIB.

With little customization, this sample provides a working security setup for CIM, which allows you to start the CIM server and users or applications to connect to the CIM server.

Please note that the CFZSEC job is meant for a quick setup only. It is not recommended to use it as the final configuration without having reviewed the details of the CIM security setup described in Chapter 6, "CIM server security setup," on page 23.

- ___ 1. Review the CFZSEC job and customize the following steps:

Required updates:

- ___ a. If profile BPX.SERVER in the FACILITY class is active on your system, you should change the UID for CFZSRV to a value other than 0 in step CRUSR. In this case, the default for the UID is 9500. If the profile is not already active on your system, it is recommended to define the CIM server user with a UID of 0 in the initial setup for simplicity reasons.

Note: Do not assign a password to the CFZSRV user ID.

- ___ b. If you are using the z/OS Resource Measurement Facility™ (RMF) optional element, replace #rkeymask with a 16-digit (0-9, A-F) keymask value to set up the connectivity between CIM and RMF via PassTickets. Otherwise, you may remove the step ENRMF from the job.

Note: The keymask value is a secret passkey. In a secure environment it is recommended to perform step ENRMF separately to avoid storing the passkey in the job log in readable format.

Optional changes:

- ___ Check that the GIDs (9501-9503) used in step CRUSR are not already in use on your system, otherwise change them.

For details on each step of the CFZSEC job see “Appendix B. Step-by-step explanation of the CFZSEC job” on page 327.

- ___ 2. Submit CFZSEC

Please note that, because this job provides a solution for each configuration, necessarily the job steps which do not apply to your system will fail. This does not affect the job's functionality.

- ___ 3. Authorize users to CIM by connecting them to group CFZUSRGP

Be sure to have at least one user authorized for CIM in order to run the Installation Verification Procedure as described in “Step 6: Running the installation verification program (IVP)” on page 22.

Security setup for a production environment

To set up the security for a production environment, see

Chapter 6, “CIM server security setup,” on page 23 and

Chapter 7, “CIM provider setup and security,” on page 37.

Step 2: Customizing the file systems and directories

On each z/OS system where you want to start the CIM server, you need to set up the directories in the UNIX file system, where the CIM server stores its configuration and runtime data:

- ___ 1. If you have installed z/OS CIM for the very first time, customize the CFZRCUST sample job from the SAMPLIB as described in “Customizing CFZRCUST” on page 46.
- ___ 2. Submit the CFZRCUST sample job from the SAMPLIB
- CFZRCUST sets up the directories */etc/wbem* and */var/wbem* for the CIM server.

- 3. Change the owner of the */etc/wbem* and */var/wbem* directories to the CIM server user (default CFZSRV). For this, enter the following commands on the UNIX System Services command prompt from a user with superuser privileges:

```
chown -R CFZSRV:CFZSRVGP /etc/wbem
chown -R CFZSRV:CFZSRVGP /var/wbem
```
- 4. If you are setting up the CIM server for a production environment, please refer to additional customization steps as described in Chapter 8, “Customization,” on page 45.

Step 3: Using default TCP/IP ports 5988 and 5989

For a successful startup, the CIM server must be able to listen to the configured HTTP or HTTPS ports. Ensure that the CIM server can use the default TCP/IP port 5988 for HTTP or 5989 for HTTPS. Check if another server is listening on one of these ports, your security product is protecting these ports, or the port is blocked by the TCP/IP configuration.

“Configuring the ports for the CIM server” on page 45 describes how you can check and, if necessary, set up the port configuration.

Step 4: Starting the CIM server

To start the CIM server,

- 1. Copy the CFZCIM started task procedure from your installation PROCLIB to a data set that is part of your PROCLIB concatenation
- 2. Start the CIM server from the z/OS system console via the START CFZCIM command

A successful start of the CIM server is indicated (among others) by the following console messages:

```
CFZ10025I: The CIM server is listening on HTTP port 5988.
CFZ10028I: The CIM server is listening on the local connection socket.
CFZ10030I: Started CIM Server version 2.10.0.
CFZ12533I: The CIM server failed to register with ARM using element name CFZ_SRV_SY1
          : return code 0x0C, reason code 0x0160.
```

For a different way to start the CIM server, see

“Customizing the CIM server startup” on page 49 and

“Running the CIM server from the UNIX System Services command prompt” on page 62.

Step 5: Customizing the UNIX System Services shell

To be able to run CIM server commands, the UNIX System Services shell has to be tailored. The file */usr/lpp/wbem/install/profile.add* contains the required environment variables to run CIM server commands.

To prepare the UNIX System Services shell to run CIM server commands,

- add the content of */usr/lpp/wbem/install/profile.add* to */etc/profile* or to the user specific profiles residing in the user home path.

For a detailed description, see “Customizing the UNIX System Services shell” on page 50.

Step 6: Running the installation verification program (IVP)

To verify that your CIM installation and customization was completed successfully, you can

- Submit the job CFZIVP contained in your installation SAMPLIB
- This job needs to run under a user that was previously authorized for CIM as described at the end of chapter “Step 1: Setting up the security for the CIM server” on page 19.

A successful CIM setup is indicated by a MAXCC=0 for the CFZIVP job along with a success message at the end of the job output like this:

```
cimivp - All tests completed successfully
```

For a detailed description of the installation verification program, see Chapter 10, “Setup verification,” on page 57.

Chapter 6. CIM server security setup

The z/OS implementation of the CIM server requires each requestor to have a real z/OS user ID. Only users who have been successfully authenticated with the z/OS security product and who have been granted access to the CIM server, will be able to execute requests against the CIM server. This chapter describes the details on how to set up these features.

Setting up security for the CIM server includes the following steps:

- 1. Define a RACF class and profile for the CIM server
(see “Defining a RACF class and profile for the CIM server” on page 24).
- 2. Define a user ID for the CIM server and grant it access to the CIM server's RACF profile
(see “Defining a CIM server user ID” on page 25)
- 3. Configure the CIM server's resource authorization model
(see “Configuring the CIM server's resource authorization model” on page 25)
- 4. Grant client users and administrators access to the CIM server
(see “Granting clients and administrators access to the CIM server” on page 28)
- 5. Allow the CIM server to surrogate for a client ID
(see “Switching identity (surrogate)” on page 29)
- 6. Optionally configure secure connections (HTTPS) for the CIM server
(see “Configuring the CIM server HTTPS connection using AT-TLS” on page 29).
- | — 7. If the APPL class for your security product is active, optionally define the
| CFZAPPL profile
| (see “Defining the CFZAPPL profile for the APPL class” on page 35)
- 8. For PassTicket usage define an encryption key for the application ID
CFZAPPL
(see “Defining an encryption key for PassTicket validation” on page 35)
- | — 9. If multilevel security (MLS) is active on your system and the CIM server
| UID≠0, grant the CIM server user ID READ access to security resource
| BPX.POE in the FACILITY class
| (see “Setting up multilevel security (MLS) support” on page 35)
- | — 10. If the CIM server is configured to use the Automatic Restart Manager
| (ARM) in a sysplex, you must ensure that the XCF address space has the
| proper authorization to perform a restart
| (see “Considering Automatic Restart Manager security” on page 36).
- | — 11. If you intend to run providers out-of-process, grant the CIM server user ID
| READ access to the profile BPX.JOBNAME defined in the FACILITY class
| (see “Running providers in separate address spaces” on page 62)

Defining a RACF class and profile for the CIM server

Access to the CIM server is controlled through RACF class WBEM. Define a new class in RACF through the dynamic CDT feature of the z/OS Security Server as follows:

- ___ 1. To be able to build the dynamic class WBEM, activate the class descriptor table (CDT) using the following RACF command:

Example:

```
SETROPTS CLASSACT(CDT) RACLIST(CDT)
```

- ___ 2. By adding a profile to the IBM class named CDT, you can create a new class definition. This profile then represents a dynamic class. The segment CDTINFO is used to define the class attributes. You can define the dynamic class WBEM with the following RACF commands:

Example:

```
RDEFINE CDT WBEM UACC(NONE) CDTINFO(  
  CASE(UPPER)  
  FIRST(ALPHA)  
  OTHER(ALPHA,NUMERIC)  
  MAXLENGTH(246)  
  MAXLENX(246)  
  KEYQUALIFIERS(0)  
  PROFILESALLOWED(YES)  
  POSIT(200)  
  DEFAULTTRC(8)  
  DEFAULTUACC(NONE)  
  RACLIST(REQUIRED)  
)  
SETROPTS RACLIST(CDT) REFRESH
```

The default values shown above (except POSIT(200)) are expected by the CIM server; do not use different values as this can yield unpredictable results.

You can ignore the warning message which is issued when adding class WBEM.

For a more detailed description of how to create a new class within RACF dynamic CDT, see *z/OS Security Server RACF Security Administrator's Guide*.

- ___ 3. To activate the new class, issue:

Example:

```
SETROPTS CLASSACT(WBEM) RACLIST(WBEM)
```

- ___ 4. After creating and activating the WBEM class, create the CIMSERV profile within this class. Profile CIMSERV is used to grant users access to the CIM server.

The following example illustrates the RACF commands that are required to define a profile named CIMSERV in this class:

Example:

```
RDEFINE WBEM CIMSERV
SETROPTS CLASSACT(WBEM) RACLIST(WBEM) REFRESH
```

Defining a CIM server user ID

To define a CIM server user ID:

- ___ 1. Either select an existing user ID or create a new CIM server user ID. We recommend to create a CIM server user ID named CFZSRV with UID 9501 and a CIM server group ID named CFZSRVGP with GID 9501.

Depending on the security model under which the CIM server runs, the user ID may need to be privileged (UID=0).

For more information to decide on the privileges for the CIM server user ID, see “Configuring the CIM server's resource authorization model.”

- ___ 2. Allow the CIM server's user ID CONTROL access to profile CIMSERV in class WBEM.

The following example shows the required RACF commands to achieve this, where the user ID CFZSRV was chosen for the CIM server:

Example:

```
PERMIT CIMSERV CL(WBEM) ACCESS(CONTROL) ID(CFZSRV)
SETROPTS CLASSACT(WBEM) RACLIST(WBEM) REFRESH
```

- ___ 3. If you run the CIM server as started task, it is recommended to define the CIM server user ID as *protected user ID*. Protected user IDs are protected from being used to log on to the system, and from being revoked through incorrect password attempts.

You can define a protected user ID or change an existing user ID into a protected user ID by assigning the NOPASSWORD, NOPHRASE, and NOOIDCARD attributes through the ADDUSER or ALTUSER command.

Example:

```
ALTUSER CFZSRV NOPASSWORD NOOIDCARD NOPHRASE
```

For more details about protected user IDs see *z/OS Security Server RACF Security Administrator's Guide*.

For more information on how to associate the CIM server user ID with the started task, see “Customizing the started task procedure CFZCIM” on page 49.

Configuring the CIM server's resource authorization model

The CIM server can be run with two different authorization models, depending on whether the profile BPX.SERVER is defined in the FACILITY class or not. In any case, the CIM server follows a *resource-based authorization model*, which means that user requests are processed in separate threads, for which the security context is switched to the user ID of the requestor or to a designated user ID. So when a CIM provider performs a user request in such a thread, it accesses any z/OS system resource under the requestor's or a designated user ID and thus,

authorization checks occur against this user ID. These checks are performed in addition to the general access check for the CIM server through the CIMSERV profile in class WBEM.

To let the resource based authorization security work properly, set up the CIM server user ID as follows:

___ 1. If the Enhanced Security model is *disabled*:

When the Enhanced Security model is disabled, no profile BPX.SERVER is active in the FACILITY class.

- ___ Set up the user ID running the CIM server as a privileged user (UID=0).

If the Enhanced Security model is *enabled*:

When the Enhanced Security model is enabled, profile BPX.SERVER exists in the FACILITY class, and the FACILITY class is active.

Note:

The definition of BPX.SERVER is not specific for the CIM server, but has system wide implications for all programs running on the z/OS system. Refer to Setting up the BPX.* FACILITY class profiles in *z/OS UNIX System Services Planning* for additional information.

- ___ a. Set up the user ID running the CIM server with UPDATE access to BPX.SERVER.
- ___ b. If the CIM server user ID is not privileged (UID ≠ 0), ensure that the directories */etc/wbem* and */var/wbem* are owned by this user ID. The following example shows how to change ownership:

Example:

```
chown -R <Server UserID>:<Server GroupID> /etc/wbem
chown -R <Server UserID>:<Server GroupID> /var/wbem
```

If any of these requirements are not met, the CIM server will not start, but issue an according error message in the logs.

- ___ 2. Consider to enable the *must-stay-clean feature* (see “Enabling the must-stay-clean feature”).
- ___ 3. If the Enhanced Security model or the must-stay-clean feature is enabled, make sure that the CIM server runs in a clean program controlled environment (see “Setting up program control” on page 27).

Enabling the must-stay-clean feature

To add additional system integrity to the CIM server, z/OS provides the optional *must-stay-clean* feature. To benefit from the feature, you must enable it explicitly.

Must-stay-clean provides additional system integrity:

- Provider libraries are loaded dynamically during runtime by the CIM server. The must-stay-clean feature prevents uncontrolled libraries to be loaded on behalf of a dynamic provider.
- Providers using the out-of-process support can be managed in separate address spaces rather than loading and calling provider libraries directly within the CIM

server process. This converts the CIM server process into a daemon process that starts off several server processes (provider agent processes). Providers are then run in threads by the provider agents.

Must-stay-clean secures the trust base between both address spaces.

To enable the must-stay-clean feature,

- define the BPX.DAEMON FACILITY class in your security product
- Defining BPX.DAEMON enforces program control. The following sample shows the according RACF commands:

Example:

```
SETROPTS CLASSACT(FACILITY)
SETROPTS RACLIST (FACILITY)
RDEFINE FACILITY BPX.DAEMON UACC(NONE)
SETROPTS RACLIST(FACILITY) REFRESH
```

Note: The definition of BPX.DAEMON is not specific for the CIM server, but has system wide implications for all programs running on the z/OS system. Refer to *Setting up the BPX.* FACILITY class profiles and Setting up security procedures for daemons in z/OS UNIX System Services Planning* for additional information.

Setting up program control

Program control means that all programs running in the address space have been loaded from a library that is controlled by a security product. A library identified to RACF program control is an example. Refer to *z/OS UNIX System Services Planning* for additional information about program control.

If the CIM server runs with authority to BPX.SERVER or with the must-stay-clean feature, the server must run in a clean program controlled environment.

To enable program control:

- 1. Ensure that all libraries are flagged as *program controlled*.

By default, all libraries shipped with the CIM server are flagged as program controlled. If additional provider libraries are installed, it may be required to set the program control flag manually using the extattr +p <libname> command.

- 2. In addition to the UNIX System Services files, mark several MVS™ libraries as program controlled. The following sample shows the according RACF commands.

Example:

```
RALT PROGRAM * ADDMEM('SYS1.SCEERUN'/'*****'/NOPADCHK) +
  UACC(READ)
RALT PROGRAM * ADDMEM('SYS1.SCEERUN2'/'*****'/NOPADCHK) +
  UACC(READ)
RDEFINE PROGRAM BLSUXTID
RALT PROGRAM BLSUXTID ADDMEM('SYS1.MIGLIB'/'*****'/NOPADCHK) +
  UACC(READ)
SETROPTS WHEN(PROGRAM) REFRESH
```

If you are using z/OS Resource Measurement Facility (RMF), then the library SYS1.SERBLINK should also be program controlled.

- ___ 3. Ensure that the CIM server runtime environment runs in its own address space:
 - ___ either start the CIM server using the provided started task procedure
 - ___ or set the environment variable `_BPX_SHAREAS=NO` in your z/OS UNIX System Services shell before starting the CIM server with the `cimserver` command.

Granting clients and administrators access to the CIM server

The CIM server authenticates users with the z/OS Security Server to determine which users can log into it. Authentication is performed for every new connection (local or remote) before a user is granted access to the CIM server.

For the CIM server for z/OS, users log on over HTTP or HTTPS using basic authentication or certificate authentication. When logging on, users are authenticated using their z/OS user ID and password as defined, for example, in RACF.

To access the CIM server, a user must be at least linked to a group with READ access to RACF profile CIMSERV. In order to use any of the administrative command-line tools of the CIM server, as described in Chapter 12, “CIM server command-line utilities and console commands,” on page 75, a group instead requires CONTROL access to the CIMSERV profile.

For detailed information about the required access rights, see the following table.

Table 2. Access types required for CIM operations

CIM operation type	CIM operations	RACF access
Basic read	GetClass, EnumerateClasses, EnumerateClassNames, GetInstance, EnumerateInstance, EnumerateInstanceNames, GetProperty, GetQualifier, EnumerateQualifier	READ
Basic write	SetProperty	UPDATE
"Method"	ExecuteMethod	UPDATE
Schema Manipulation	CreateClass, ModifyClass, DeleteClass	CONTROL
Instance Manipulation	CreateInstance, ModifyInstance, DeleteInstance	UPDATE
Indication Subscription	CreateInstance, ModifyInstance, DeleteInstance	UPDATE
Association Traversal	Associators, AssociatorNames, References, ReferenceNames	READ
Query	ExecQuery	READ
Qualifier Declaration	SetQualifier, DeleteQualifier	CONTROL

The following example shows how to define UPDATE access for a client group called CFZUSRGP:

Example:

```
PERMIT CIMSERV CL(WBEM) ACCESS(UPDATE) ID(CFZUSRGP)
SETROPTS RACLIST(WBEM) REFRESH
```

In addition, the CIM server user ID must be defined as a surrogate of the client user ID (see “Switching identity (surrogate)”).

To enable a user to use the command line tools, set up the UNIX System Services environment as described in “Customizing the UNIX System Services shell” on page 50.

Switching identity (surrogate)

The CIM server uses services which can be run in client or server security context. For this, the CIM server must be able to switch its user ID to the client user ID. To allow the CIM server for this, define BPX.SRV profiles for the SURROGAT class within your System Authorization Facility (SAF).

The recommended way to do this is:

- Specify a general profile to allow the CIM server user ID to switch to any other z/OS user ID with a UNIX System Services segment defined.

The following sample shows the required RACF commands to create the generic profile, where the CIM server user ID is CFZSRV:

Example:

```
SETROPTS CLASSACT(SURROGAT) RACLIST(SURROGAT) GENERIC(SURROGAT)
RDEFINE SURROGAT BPX.SRV.** UACC(NONE)
PERMIT BPX.SRV.** CLASS(SURROGAT) ACCESS(READ) ID(CFZSRV)
SETROPTS GENERIC(SURROGAT) RACLIST(SURROGAT) REFRESH
```

Configuring the CIM server HTTPS connection using AT-TLS

The CIM server runtime environment can profit from the Application Transparent Transport Layer Security (AT-TLS) functionality. The communication between the CIM client and the CIM server can be secured by encryption (SSL). Additionally the CIM client can be authenticated by a certificate and mapped to a local z/OS user ID.

The following task describes how to configure the CIM server HTTPS connection using AT-TLS.

— 1. **Prerequisites**

- Ensure that the basic setup for the Policy Agent is done.
See *z/OS Communications Server: IP Configuration Guide* about policy-based networking and data protection.
- Ensure that the basic certificates setup is done.
For handling certificates for secure communications for RACF, see *z/OS Security Server RACF Security Administrator's Guide* about RACF and digital certificates.

— 2. **Configuring the CIM server runtime**

- Set the configuration property *enableHttpsConnection* to true.
- Ensure that the configuration property *httpsPort* is set to 5989. This default should not be changed.
- Ensure that the https port 5989 can be used by the CIM server. For more information, see “Configuring the ports for the CIM server” on page 45.

Based on this configuration, the CIM server opens a second listener for receiving client connections and ensures that these connections are secured by AT-TLS. The level of protection depends on the configuration of AT-TLS. If a connection on this port is not secured by AT-TLS, the connection is closed and an appropriate error message is issued on the operator console.

— 3. **Configuring the Policy Agent to secure communication for the CIM server**

- Enable the Policy Agent for AT-TLS.
See *z/OS Communications Server: IP Configuration Guide* about Application Transparent Transport Layer Security data protection.
- Configure the Policy Agent to secure the communication for the CIM server at the configured HTTPS port (configuration property *httpsPort*). For sample Policy Agent policies, see “Example: Configuring AT-TLS for secure communication” to configure either an SSL protection or an SSL protection including a certificate based authentication.
- Optionally you can protect the (outgoing) indication delivery on a specific port range with SSL.

Example: Configuring AT-TLS for secure communication

This sample shows the exemplary setup of the Policy Agent to secure communication for the CIM server.

- SSL protection only (see “Prerequisite: Common certificate setup” and “SSL protection only” on page 31)
- SSL protection including certificate based authentication (see “Prerequisite: Common certificate setup” and “SSL protection including certificate based authentication” on page 31)
- SSL protected indication delivery (see “Prerequisite: Common certificate setup” and “SSL protected indication delivery” on page 33)

For a more detailed explanation about Policy Agent AT-TLS policy see *z/OS Communications Server: IP Configuration Reference* about Policy Agent and policy applications and Application Transparent Transport Layer Security (AT-TLS) policy statements.

Prerequisite: Common certificate setup

To enable AT-TLS to secure the communication, a valid server certificate, the associated server private key, and the certificate of trusted Certificate Authority's (CA) are needed. These examples are using a key ring named *CFZCIMServerRing* to store these credentials. This key ring must be accessible by the CIM server user ID (e.g. *CFZSRV*), and the server certificate must be the default certificate.

For a sample setup with RACF, see *z/OS Security Server RACF Security Administrator's Guide* about RACF and digital certificates, implementation scenario 1 or 2. For handling certificates and key rings, please refer to the documentation of your SAF product.

SSL protection only

Simple SSL protection means that the communication between the client and the server is encrypted without having established a trust relationship between the client and the server. So the client still needs to send a user ID and a password for authentication.

To set up AT-TLS with simple SSL protection for the CIM server, a policy for the Communications Server Policy Agent has to be created that restricts AT-TLS to the CIM server port 5989 and to inbound TCP/IP communication.

Sample Policy Agent policy for a simple SSL protection:

Example

```
TTLRule          CFZCIMServerRuleInbound
{
    Jobname          CFZCIM*
    LocalPortRange    5989
    Direction         Inbound
    TLSGroupActionRef grp_StartUp
    TLSEnvironmentActionRef CFZCIMServerEnvActionInbound
}

TLSEnvironmentAction CFZCIMServerEnvActionInbound
{
    HandshakeRole      Server
    TLSEnvironmentAdvancedParms
    {
        ClientAuthType  PassThru
    }
    TLSKeyRingParms
    {
        Keyring          CFZCIMServerRing
    }
}

# Common StartUp Group that new Rules may use
# Shows how each connection maps to policy
TLSGroupAction grp_StartUp
{
    TLSEnabled On
    Trace 0          # Log Errors and Info messages to syslogd
}
```

CIM server specific notes to the AT-TLS Policy parameters:

TTLRule: Jobname

Jobname identifies where this rule applies. In the example, it is the started task job name. If you set up the connection this way, the configuration does not influence other parts of the system.

TTLRule: LocalPortRange

This property must match the HTTPS port definition of the CIM server.

SSL protection including certificate based authentication

Since the CIM server is aware of AT-TLS, you can use SSL secured communications and certificates based authentication between the CIM client and the CIM server. The CIM server queries AT-TLS if the client is identified by a client certificate and mapped to a local user ID.

Authentication based on SSL certificates means:

- the communication between the client and the server is encrypted,
- the trust relationship is established, and
- the client certificate is matched to a local z/OS user ID.

No user ID and password have to be provided by the client. All subsequent authorization checking is done with the mapped user ID.

The CIM client sends an SSL certificate to AT-TLS, AT-TLS sends the certificate to RACF and RACF associates the certificate to the appropriate user ID, which then can access the CIM server. Vice versa, the CIM server returns its responses to client requests using SSL certificates.

This method of authentication provides more security than sending user IDs and passwords between client and server.

If you want to use this enhanced method based on certificates, you must create the inbound/outbound rules as follows:

To set up AT-TLS with authentication based on SSL certificates for the CIM server, a policy for the Communications Server Policy Agent has to be created that restricts AT-TLS to the CIM server port 5989 and to inbound TCP/IP communication. Also the SAF facility has to be set up to match certificate subjects to local z/OS user IDs.

For setting up the SAF facility to map certificates to local user IDs, see *z/OS Security Server RACF Security Administrator's Guide* about RACF and digital certificates, Certificate Name Filtering.

Sample Policy Agent policy for authentication based on SSL certificates:

Example

```
TTLRule CFZCIMServerRuleInbound
{
  Jobname CFZCIM*
  LocalPortRange 5989
  Direction Inbound
  TLSGroupActionRef grp_StartUp
  TLSEnvironmentActionRef CFZCIMServerEnvActionInbound
}

TLSEnvironmentAction CFZCIMServerEnvActionInbound
{
  HandshakeRole ServerWithClientAuth
  TLSEnvironmentAdvancedParms
  {
    ClientAuthType SAFCheck
  }
  TLSKeyRingParms
  {
    Keyring CFZCIMServerRing
  }
}

# Common StartUp Group that new Rules may use
# Shows how each connection maps to policy
TLSGroupAction grp_StartUp
{
  TLSEnabled On
  Trace 0 # Log Errors and Info messages to syslogd
}
```

CIM server specific notes to the AT-TLS Policy parameters:

TTLSRule: Jobname

Jobname identifies where this rule applies. In this example it is the started task job name. If you set up the connection this way, the configuration does not influence other parts of the system.

TTLSRule: LocalPortRange

This property must match the HTTPS port definition of the CIM server.

SSL protected indication delivery

This sample shows an exemplary setup for the usage of RACF to deliver secured indications with AT-TLS.

Delivering secured indications from the CIM server to an indication listener means that the CIM server establishes an encrypted connection to deliver indications. Whether a trusted relationship is established or not depends on the listener configuration.

In case a trusted relationship is established, the CIM server is a client to the indication listener and therefore an outbound policy has to be specified with AT-TLS. To deliver secured indications, the job name of the CIM server and the port specified in the indication handler destination property must match. An indication is defined by the application programmer so there has to be an agreement between the application programmer and the system programmer that port secured indications are sent from the CIM server to the indication listeners.

Sample Policy Agent policy for the delivery of secured indications:

Example

```

TTLRule          CFZCIMServerRuleOutbound
{
    Jobname          CFZCIM*
    RemotePortGroupRef CFZCIMServerRemotePortGroup
    Direction        Outbound
    TLSGroupActionRef grp_StartUp
    TLSEnvironmentActionRef CFZCIMServerEnvActionOutbound
}

TLSEnvironmentAction CFZCIMServerEnvActionOutbound
{
    HandshakeRole      Client
    TLSKeyRingParms
    {
        Keyring CFZCIMServerRing
    }
}

PortGroup        CFZCIMServerRemotePortGroup
{
    PortRange
    {
        Port 5989
    }

    PortRange
    {
        Port 6000-7000
    }
}

# Common StartUp Group that new Rules may use
# Shows how each connection maps to policy
TLSGroupAction grp_StartUp
{
    TTLEnabled On
    Trace 0          # Log Errors and Info messages to syslogd
}

```

CIM server specific notes to the AT-TLS Policy parameters:

TTLRule: Jobname

Jobname identifies where this rule applies. In this example it is the started task job name. If you set up the connection this way, the configuration does not influence other parts of the system.

PortGroup

All indications which do have a port specified within the indication handler destination property and do match to any PortRange defined within the PortGroup are delivered secure via AT-TLS. If the destination property protocol is specified as https and no other port is specified, port 5989 will be used by the CIM server. So please ensure that always port 5989 is within a PortRange. In this example, all indications with port 5989 and port 6000-7000 are delivered in a secured way.

Defining the CFZAPPL profile for the APPL class

If the APPL class for the security product is active, the CFZAPPL profile can be defined to allow only certain users to log on to the CIM server. You can manage access to the CIM server application by a profile for CFZAPPL in the APPL class with an access list that contains only those users who are allowed to use the CIM server.

In general, you need not define a profile for CFZAPPL unless you have a generic profile (*) that prevents access to applications without a more specific profile.

Defining an encryption key for PassTicket validation

The CIM server can alternatively validate a user ID and a PassTicket instead of a user ID and a password for authentication.

For more information about PassTickets, see *z/OS Security Server RACF Security Administrator's Guide*.

A PassTicket is validated against an application ID. The application ID for the CIM server is CFZAPPL.

To enable CFZAPPL for the CIM server,

— Define CFZAPPL profile in the PTKTDATA class in RACF.

Example:

```
SETROPTS CLASSACT (PTKTDATA)
SETROPTS RACLIST (PTKTDATA)
RDEFINE PTKTDATA CFZAPPL -
                SSIGNON(KEYMASKED(<key>))
SETROPTS RACLIST(PTKTDATA) REFRESH
```

where <key> is the 16 digit encryption key.

Setting up multilevel security (MLS) support

In a conventional CIM server setup, all providers are processed in the CIM server's address space. If the CIM server is running in a *multilevel secure (MLS)* z/OS system, providers are executed in several provider agent processes depending on the user's security classification and port of entry, independent of the CIM server configuration.

Additional setup for an MLS environment:

— If the Enhanced Security model is enabled (that is, the CIM server user ID is not privileged), make sure that the CIM server user ID has READ access to security resource BPX.POE in the FACILITY class.

This allows the CIM server to use the z/OS XL C/C++ Run-Time Library function `__poe()` to retrieve information on the security classification and the port of entry of a user.

Example for the security product RACF:

```
RDEFINE FACILITY BPX.POE UACC(NONE)
PERMIT BPX.POE CL(FACILITY) ACCESS(READ) ID(CFZSRV)
SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY) REFRESH
```

where CFZSRV is the CIM server user ID.

For general information on MLS, please refer to *z/OS Planning for Multilevel Security and the Common Criteria*.

If the CIM server is not running in an MLS z/OS system, and you want to run providers in processes separate from the CIM server process for stability reasons or for debugging purposes, use the out-of-process support for providers. For more information, see “Running providers in separate address spaces” on page 62.

Considering Automatic Restart Manager security

The z/OS CIM server is enabled for the Automatic Restart Manager (ARM).

If the CIM server is configured to use ARM in a sysplex, you must ensure that the XCF address space has the proper authorization to perform a restart. ARM must be able to issue operator commands from the XCF address space (XCFAS) to start the CIM server.

The CIM server is not running in supervisor mode. Therefore, the user ID running the CIM server must have proper SAF authorization to be allowed to register to ARM. Therefore the user ID running the CIM server also needs the SAF authorization for UPDATE access to the following FACILITY class resource:

Example:

```
IXCARM.DEFAULT.CFZ_SRV_<system_name>
```

Here is an example for entitling the CIM server user ID CFZSRV to register the CIM server for all machines within a sysplex using RACF:

Example:

```
SETROPTS CLASSACT(FACILITY) GENERIC(FACILITY)
SETROPTS RACLIST(FACILITY)

RDEFINE FACILITY IXCARM.DEFAULT.CFZ_SRV_* UACC(NONE)

PERMIT IXCARM.DEFAULT.CFZ_SRV_* CLASS(FACILITY) +
      ID(CFZSRV) ACCESS(UPDATE)

SETROPTS RACLIST(FACILITY) REFRESH
```

Chapter 7. CIM provider setup and security

This chapter describes additional security and setup requirements for providers:

- ___ 1. RMF provider
(see “Setting up the CIM server for RMF monitoring”)
- ___ 2. Network providers
(see “Setting up the CIM server for network providers” on page 38)
- ___ 3. Job, Cluster, and Monitoring providers
(see Chapter 14, “z/OS Management Instrumentation for CIM,” on page 121)
- ___ 4. Cluster, CoupleDataset, and JES2-JES3Jobs providers
(see “Setting up the CIM server for Cluster, CoupleDataset, and JES2-JES3Jobs providers” on page 38)
- ___ 5. WLM provider
(see “Setting up the CIM server for WLM management” on page 40)
- ___ 6. Storage management providers
(see “Setting up the CIM server for storage management” on page 41)
- ___ 7. Optionally, you can run providers in a designated user context
(see “Running providers in a designated user context” on page 42)
- ___ 8. Optionally, you can choose the provider based authorization model
(see “Utilizing the provider based authorization model” on page 43)

Setting up the CIM server for RMF monitoring

If you have installed RMF, you should consider the following setup for the connection of your RMF CIM providers to the RMF Distributed Data Server (DDS).

- ___ 1. The CIM monitoring providers can automatically locate an active RMF DDS in the sysplex. When the DDS is restarted on different systems through RMF management, or through manual action, the CIM monitoring providers can connect to an active DDS without additional configuration. To enable this option, comment out or omit the RMF_CIM_HOST environment variable from your cimserver.env file.

For more information on the RMF-managed DDS refer to “Starting the Distributed Data Server” in the *z/OS RMF User’s Guide*.

- ___ 2. The CIM monitoring providers support PassTicket authentication to the DDS. In this case the HTTP_NOAUTH option must be disabled. Secure signon through PassTickets needs to be enabled in your security manager.

If you are using z/OS Security Server (RACF), the following commands can be used (for more information about configuring RACF to use PassTicket services, refer to *z/OS Security Server RACF Security Administrator’s Guide*):

- ___ Activate the PTKTDATA class and the SETROPTS RACLIST processing:

Example for RACF:

```
SETROPTS CLASSACT(PTKTDATA) RACLIST(PTKTDATA) GENERIC(PTKTDATA)
```

- Define the application GPMSEVER to your security product.
The application is defined through the SAF profile GPMSEVER in class PTKTDATA. <keymask> is the secret passkey shared with the application.

Example for RACF:

```
RDEFINE PTKTDATA GPMSEVER SSGNON(KEYMASKED(<keymask>))  
SETROPTS RACLIST(PTKTDATA) REFRESH
```

- Define an access profile for the PassTicket service.

Example for RACF:

```
RDEFINE PTKTDATA IRRPTAUTH.GPMSEVER.* UACC(NONE)
```

- Grant the CIM server UPDATE access to the generic profile IRRPTAUTH.GPMSEVER.* in class PTKTDATA.
This enables the CIM server user to create PassTickets on behalf of other users for authentication with GPMSEVER.

Example for RACF:

```
PERMIT IRRPTAUTH.GPMSEVER.* CL(PTKTDATA) ID(CFZSRV) ACCESS(UPDATE)
```

- Activate the changes.

Example for RACF:

```
SETROPTS RACLIST(PTKTDATA) REFRESH
```

Setting up the CIM server for network providers

Access to TCP/IP stack data is controlled by a security resource. Such a security resource is required if a user ID, associated with the client of the CIM server, is not defined as a z/OS UNIX superuser. The resource name is **EZB.CIMPROV.sysname.tcpname**. It is defined in the SERVAUTH class. Access is granted if the user ID associated with the client of the CIM server is permitted for READ access to the resource.

Setting up the CIM server for Cluster, CoupleDataset, and JES2-JES3Jobs providers

For using the Job and Cluster providers, some additional setup has to be done.

- 1. Configure the Common Event Adapter (CEA):
 - a. Define additional parameters in PARMLIB (see “PARMLIB updates” on page 39)
 - b. Prepare RACF for CEA (see “RACF setup” on page 39)
- 2. When running in a sysplex, format the sysplex couple dataset to allow it to be cluster capable (see “Sysplex couple dataset formatting” on page 39).

PARMLIB updates

To enable the Job and Cluster providers, define the following PARMLIB parameters:

MAXCAD limit

This parameter defaults to 50. If the installation sets a lower limit, it may be necessary to increase this setting to accommodate the Common Event Adapter (CEA) Common Area Data Space (CADS).

APF Authorize SYS1.MIGLIB

To enable the CFRM-related CIM providers, add the following to the installation's PROGxx PARMLIB member:

```
APF ADD DSNAME(SYS1.MIGLIB) VOLUME(*****)
```

REXX Alternate Library

The Couple Dataset providers require the use of compiled REXX execs provided as part of the z/OS 1.9 SYSREXX support. These execs require the use of the REXX alternate library. The following addition to the installation's PROGxx PARMLIB member is one way to accomplish this:

```
LNKLST ADD,NAME(LNKLST00),DSN(REXX.V1R3M0.SEAGALT),ATTOP
```

RACF setup

For using the Job and Cluster providers, RACF has to be prepared for CEA:

- ___ 1. For the necessary RACF setup to permit CEA to use Automatic Restart Manager (ARM), see *z/OS Planning for Installation*, chapter "Customizing for CEA".
- ___ 2. To configure CEA for the Cluster, Couple Dataset and JES2/JES3 Jobs CIM providers, use job CFZSEC from the installation SAMPLIB as described in Chapter 5, "Quick guide: CIM server setup and verification," on page 19. For details see job steps PECEA and ENCLCDS in "Appendix B. Step-by-step explanation of the CFZSEC job" on page 327.

Sysplex couple dataset formatting

To format the sysplex couple dataset, use the IXCL1DSU format utility by specifying:

```
ITEM NAME(CLUSTER) NUMBER(1)
```

The following table shows a sample JCL formatting the sysplex couple dataset for enabling cluster functions. The IXCSYSPF member has been updated to indicate the new CLUSTER keyword.

Table 3. Sample sysplex couple dataset formatting JCL

```

IXCSYSPF JOB
*
* SAMPLE JCL TO FORMAT THE PRIMARY AND/OR ALTERNATE COUPLE DATA SETS
* - SYSPLEX COUPLE DATA SETS
*
* 1. SYSPLEX NAME IS REQUIRED AND IS 1-8 CHARACTERS
* 2. SYSPRINT DD IS A REQUIRED DD STATEMENT FOR FORMAT UTILITY
*   MESSAGES
* 3. SYSIN DD IS A REQUIRED DD STATEMENT FOR FORMAT UTILITY CONTROL STATEMENTS
*
//STEP1 EXEC PGM=IXCL1DSU
//STEPLIB DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
        DEFINEDS SYSPLEX(PLEX1)
                DSN(SYS1.XCF.CDS01) VOLSER(CDSPK1)
                MAXSYSTEM(8)
                CATALOG
        DATA TYPE(SYSPLEX)
                ITEM NAME(GROUP) NUMBER(50)
                ITEM NAME(MEMBER) NUMBER(120)
                ITEM NAME(GRS) NUMBER(1)
                ITEM NAME(CLUSTER) NUMBER(1)
        DEFINEDS SYSPLEX(PLEX1)
                DSN(SYS1.XCF.CDS02) VOLSER(CDSPK1)
                MAXSYSTEM(8)
                CATALOG
        DATA TYPE(SYSPLEX)
                ITEM NAME(GROUP) NUMBER(50)
                ITEM NAME(MEMBER) NUMBER(120)
                ITEM NAME(GRS) NUMBER(1)
                ITEM NAME(CLUSTER) NUMBER(1)
/*

```

Setting up the CIM server for WLM management

The z/OS Workload Manager (WLM) subsystem is represented in z/OS CIM through class IBMzOS_WLM.

The provider serving class IBMzOS_WLM requires UPDATE access to resources which are protected by profile MVSADMIN.WLM.POLICY in class FACILITY.

- Permit access to MVSADMIN.WLM.POLICY by either permitting the requestor's user ID access to the discrete profile MVSADMIN.WLM.POLICY, or to one of the generic umbrella profiles MVSADMIN.WLM.* or MVSADMIN.*, depending on your system's current security definitions.
- Either, grant the requestor's user ID UPDATE access to the discrete RACF profile MVSADMIN.WLM.POLICY in class FACILITY.

Example:

```

SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY)
PERMIT MVSADMIN.WLM.POLICY CLASS(FACILITY) ID(<client-ID>) ACCESS(UPDATE)
SETROPTS RACLIST(FACILITY) REFRESH

```

- Or, grant the requestor's user ID UPDATE access to generic RACF profile MVSADMIN.WLM.* in class FACILITY.

Example:

```
SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY) GENERIC(FACILITY)
PERMIT MVSADMIN.WLM.* CLASS(FACILITY) ID(<client-ID>) ACCESS(UPDATE)
SETROPTS RACLIST(FACILITY) REFRESH
```

— If your system's environment is set up for program control, the load module BLDUXTID in SYS1.MIGLIB needs to be program controlled. The following example shows how you can enable program control for load module BLSUXTID.

Example:

```
RDEFINE PROGRAM BLSUXTID
RALT PROGRAM BLSUXTID ADDMEM('SYS1.MIGLIB'/'*****'/NOPADCHK) +
UACC(READ)
SETROPTS WHEN(PROGRAM) REFRESH
```

A complete example for the security setup required by the CIM provider for class IBMzOS_WLM is provided in the z/OS CIM sample security setup job CFZSEC, step ENWLM.

More information:

Chapter 15, “WLM classes,” on page 261

“Step ENWLM” on page 336

Setting up the CIM server for storage management

The IOS services IOSCDR and IOSCHPD have been extended for z/OS 1.13 to facilitate the retrieval of the world wide port number (WWPN) for the Initiator (IOSCHPD) and Target (IOSCDR) protocol endpoints of IBMzOS_SBProtocolEndPoint. The retrieval of the WWPN through IOSCDR is only possible under the following conditions:

- 1. The used hardware is at least an IBM System z10™.
- 2. The requestor or CIM client has UPDATE access to the IOSCDR profile in the FACILITY class.

Example:

```
SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY)

RDEFINE FACILITY IOSCDR UACC(NONE)
PERMIT IOSCDR CL(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)

SETROPTS RACLIST(FACILITY) REFRESH
```

The SMI-S CIM life cycle indications are using the Common Event Adapter (CEA) to be notified for device path changes and insertions or deletions of FICON® channel ports.

The following setup has to be done to grant the CIM server access to CEA for the retrieval of events and IOS information:

- 1. Ensure that the CEA is running in full function mode.

- ___ 2. Grant the CIM server user ID UPDATE access to the IOSCDR profile in the FACILITY class.

Example:

```
SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY) GENERIC(FACILITY)

RDEFINE FACILITY IOSCDR UACC(NONE)
PERMIT IOSCDR CL(FACILITY) ID(CFZSRV) ACCESS(UPDATE)

SETROPTS RACLIST(FACILITY) REFRESH
```

- ___ 3. The SMI-S CIM life cycle indications are using CEA to be notified of device path changes and insertions or deletions of FICON channel ports. Event notification from CEA is protected through the following profiles in the RACF class SERVAUTH:

- CEA.CONNECT
- CEA.SUBSCRIBE.ENF_0009*
- CEA.SUBSCRIBE.ENF_0027*
- CEA.SUBSCRIBE.ENF_0033*

To be permitted to subscribe for event notification by CEA the CIM server user ID requires READ access to these mentioned profiles. To keep your security setup simpler it is recommend to protect the CEA resources using the generic profile CEA.* instead of defining the several discrete profiles.

Grant the CIM server user ID READ access to the generic profile CEA.* in RACF class SERVAUTH:

Example:

```
SETROPTS CLASSACT(SERVAUTH) RACLIST(SERVAUTH) GENERIC(SERVAUTH)
RDEFINE SERVAUTH CEA.* UACC(NONE)
PERMIT CEA.* CLASS(SERVAUTH) ID(CFZSRV) ACCESS(READ)
SETROPTS RACLIST(SERVAUTH) REFRESH
```

Running providers in a designated user context

Generally, the vendor of a provider (implementing a certain CIM class) defines if a provider should run under a designated user context and also supplies the according documentation describing the specific setup steps.

When an invocation is caused by an external CIM operation, by default the provider is processed in the context of the *requestor's user ID*. As the provider runs under the identity of the requestor's user ID, all resource access authorization occurs against this user ID. So the requestor must be authorized for all resources that a provider accesses during a request.

To avoid that a CIM client user ID needs global access to all the resources that a provider uses for gathering data, a provider can be registered with a *designated user ID*. The designated user ID specifies a separate security context which is used to process the provider. The designated user ID must be authorized to access all the resources accessed by the provider. Instead of directly using a requestor's user ID when accessing the resource, the provider code now has to perform custom authorization checks based on the requestor's user ID, to prevent unauthorized access to resources. The security definitions for the designated user ID should be

similar to those of regular client users, as described in “Switching identity (surrogate)” on page 29, but it is recommend to make the designated user ID a protected user ID by disabling password, passphrase and oidcard.

Example:

```
ALTUSER <designated-user-ID> NOPASSWORD NOOIDCARD NOPHRASE
```

The properties *UserContext* and *DesignatedUserContext* of CIM class *PG_ProviderModule* specify the provider's processing context. You can specify the values for these properties in the provider registration MOF file for each provider module. By default, it is installed at `/usr/lpp/wbem/provider/schemas/...` For further details, see “*PG_ProviderModule*” on page 281.

Utilizing the provider based authorization model

When the provider based authorization model is enabled for a provider, a provider-specific profile in SAF class WBEM restricts the access to the provider. In this case, the requesting user ID needs special authorization before it can invoke the provider. These checks are strongly recommended for providers which use a designated user ID.

Each CIM operation needs, depending on its type, a different level of access to the security profile. For example, in order to access CIM operations that change the states of objects, WRITE access to the SAF profile defined for a provider is required. Schema manipulation is only available to users with CONTROL access to SAF profile CIMSERV in class WBEM.

You can define provider based authorization by relating a SAF profile in class WBEM to a single provider library. The specific SAF requirements of the provider should be documented. Unless instructed to do so, there is no need to take any configuration action for this.

To correlate a provider and a SAF profile, define a security access profile. The OpenPegasus CIM class *PG_Provider* contains a string type attribute named *SecurityAccessProfile*. Providers that register with an instance of class *PG_Provider* containing the *SecurityAccessProfile* property, must specify their SAF profile with this property in order to define it to the system. In addition, requesting users must have the according level of authorization for the named profile.

If you want to have an existing provider exploit this feature,

- 1. remove (unregister) the provider using the *cimprovider* utility
- 2. add the security profile name in property *SecurityAccessProfile* in the provider registration MOF file
- 3. register the provider again

The existence of a specified security profile is not checked during provider registration, but during runtime, when a request is received for the according provider.

More information:

Table 2 on page 28 lists the type of access required for the different types of CIM operations

“*cimprovider*” on page 81

	"Registering a provider with the CIM server" on page 277
	"PG_Provider" on page 280

Chapter 8. Customization

This chapter describes the customization tasks you should consider before you start the CIM server for the first time:

- 1. Make sure that the CIM server can use the configured HTTP and HTTPS ports (usually, port numbers 5988 and 5989)
(see “Configuring the ports for the CIM server”).
- 2. If you have installed z/OS CIM for the very first time, ensure that CFZRCUST has been customized during CIM server setup. If you have not already done so, it is now time to customize CFZRCUST
(see “Customizing CFZRCUST” on page 46).
- 3. Ensure that you have run CFZRCUST during CIM server setup. If you have not already done so, it is now time to run CFZRCUST.
- 4. Customize the CIM server startup
(see “Customizing the CIM server startup” on page 49).
- 5. Customize the UNIX System Services shell to be able to run CIM server commands
(see “Customizing the UNIX System Services shell” on page 50).
- 6. Customize the environment variables
(see “Setting the CIM server environment variables” on page 51).
- 7. Select a WLM service class for z/OS CIM priority
(see “Selecting a WLM service class for z/OS CIM priority” on page 52).

Configuring the ports for the CIM server

Ensure that the CIM server can use the default port 5988 for HTTP or 5989 for HTTPS. You can change the default values for the ports using the *httpPort* and *httpsPort* CIM server configuration properties.

When the CIM server cannot listen to one of the ports, the CIM server startup will fail. Then check if another server is listening to the ports, your security product is protecting the ports, or the ports are blocked by the TCP/IP configuration.

- To identify your currently configured port for HTTP and HTTPS, see the configuration properties *httpPort* and *httpsPort* as described in Chapter 9, “CIM server configuration,” on page 53.
- Use the TCP/IP NETSTAT ALLCONN PORT command to check for servers using the specified ports.

Example:

```
TSO NETSTAT ALLCONN (PORT 5988
```

- Your security product may also need to be configured to allow access to the HTTP port. For example, OEM security product ACF2 may require “Stack & Port security authorization” for the CIM server.

Please refer to your security product's documentation for additional information.

— The TCP/IP PORT and PORTRANGE statements in the TCP/IP profile may be used to make the configured HTTP port available for the CIM server's use.

For more information, refer to *z/OS Communications Server: IP Configuration Reference*, chapter "TCP/IP profile (PROFILE.TCPIP) and configuration statements".

Customizing CFZRCUST

The job CFZRCUST installs and migrates the z/OS CIM server configuration and repository on each target machine. A sample of CFZRCUST is shipped with the default SAMPLIB.

If you have installed z/OS CIM for the first time, you need to customize CFZRCUST.

Prerequisites

- 1. The target system is running with configured UNIX System Services.
- 2. The CIM server is stopped.
- 3. The user running this job
 - must either have UNIX user ID 0
 - or must be able to copy files and set the program control bit on files.
- 4. If you intend to mount the data set on a separate file system - which is recommended - this user must be entitled to allocate a 100 MB zFS data set (if not yet allocated), and must be authorized to mount file systems.

Now you have to adjust the sample job CFZRCUST, which is located in the SAMPLIB, to fit your environment. There are two options you can choose; it depends on whether you want to place the CIM server repository and the log files in a separate file system or not.

Option 1: Placing /var/wbem in a separate file system

To place the CIM server repository and the log files in a separate file system, perform the following steps. For a better maintainability, it is recommended to mount a separate file system on */var/wbem* for the CIM server's data repository. The recommended size is 100 MB.

- 1. Adjust the job card.
- 2. Adjust STEP 1 of the JCL to create a file system data set. Choose this step to create a data set. You must provide the name in the JCL for further processing the selected sample job.

As an alternative, you can also create the file system outside of this JCL.

STEP 1 is a sample to allocate a zFS file system dataset:

JCL - sample STEP 1

```
/******  
/* STEP 1 - Create zFS DataSet for /var/wbem */  
/******  
//DEFZFS EXEC PGM=IDCAMS  
//SYSPRINT DD SYSOUT=*  
//DASD0 DD DISP=(NEW,CATLG),UNIT=unit,VOL=SER=volser  
//SYSIN DD *  
    DEFINE CLUSTER( -  
        NAME(%CFZVARWBEMDS%) -  
        VOLUMES(volser) -  
        STORAGECLASS(OMVS) -  
        LINEAR -  
        CYLINDER(150 15) -  
        SHAREOPTIONS(3) -  
    )  
//FRMZFS EXEC PGM=IOEAGFMT,REGION=0M,  
// PARM=(' -aggregate %CFZVARWBEMDS% -compat ')  
//SYSPRINT DD SYSOUT=*  
//STDOUT DD SYSOUT=*  
//SYSPRINT DD SYSOUT=*  
//SYSPRINT DD SYSOUT=*
```

- ___ 3. If you are using an extensible file system, you can suppress the check for enough free space by specifying the parameter `-noSpaceCheck` in the installation/migration utility at STEP 2 of the JCL. The system administrator is responsible to ensure that there is enough free space (60 MB) available for installation or migration, otherwise the job will fail. This will not suppress the check if you use a separate file system data set.

The beginning of STEP 2 will then look like:

JCL - sample STEP 2

```
/******  
/* STEP 2 - Run customization/migration utility */  
/******  
//CFZRCUST EXEC PGM=BPXBATCH,TIME=NOLIMIT,REGION=0M,  
// PARM='PGM /usr/lpp/wbem/install/CFZRCUST.sh -noSpaceCheck'  
//*
```

- ___ 4. Replace the place holder `%CFZVARWBEMDS%` in the JCL with the name of the file system data set, for example: `OMVS.VARWBEM.ZFS`.

When you have submitted the job, a return code (MAXACC) 0 or 4 indicates a successful installation or migration. If the return code is 12, look at the job output, correct the error and submit the job again.

- ___ 5. To mount the file system for the CIM server's data repository, you can add a mount statement in your BPXPRMxx PARMLIB member:

Mount statement:

```
MOUNT FILESYSTEM(OMVS.VARWBEM.ZFS)  
    TYPE(ZFS)  
    MOUNTPPOINT('/var/wbem')  
    MODE(RDWR)
```

Option 2: Using an existing file system for /var/wbem

To use an existing file system for the CIM server repository and the log files, perform the following steps:

- ___ 1. Adjust the job card.
- ___ 2. Omit STEP 1 of the sample job and specify the parameter -noDS in the installation/migration utility at STEP 2 of the JCL.-noDS disables the use of a separate file system dataset for /var/wbem.

JCL - sample STEP 2

```
/******  
/* STEP 2 - Run customization/migration utility      */  
/******  
//CFZRCUST EXEC PGM=BPXBATCH,TIME=NOLIMIT,REGION=0M,  
//          PARM='PGM /usr/lpp/wbem/install/CFZRCUST.sh -noDS'  
/*
```

- ___ 3. If you are using an extensible file system, you can suppress the check for enough free space by specifying the parameter -noSpaceCheck in the installation/migration utility at STEP 2 of the JCL. The system administrator is responsible to ensure that there is enough free space (60 MB) available for installation/migration, otherwise the job will fail. This will not suppress the check if you use a separate file system data set.

When you have submitted the job, a return code (MAXACC) 0 or 4 indicates a successful installation or migration. If the return code is 12, look at the job output, correct the error and submit the job again.

System specific directories

After successfully running CFZRCUST, the following files are located on your system:

Table 4. Installation directories for z/OS CIM

Directory	Description	Owner	Access
/etc/wbem	This directory is system specific and used by the CIM server to store its configuration files and environment for the started task. It has to be owned and writable by the CIM server user (e.g. CFZSRV)	CIM server user	rwxr-xr-x
/var/wbem	This directory is system specific. The CIM server uses it to store its data repository for CIM classes and instances as well as for various files used at runtime, such as the special file required for connecting to the CIM server through UNIX Domain Sockets (cimxml.socket). This directory has to be owned by the CIM server user and only the CIM server user must have write access to it.	CIM server user	rwxr-xr-x
/var/wbem/ logs	Used by the CIM server to log the stdout and stderr output when running as a started task. See "Customizing the started task procedure CFZCIM" on page 49 for details.	CIM server user	rwxr-xr-x

If the CIM server user ID is not privileged (UID \neq 0), ensure that the directories */etc/wbem* and */var/wbem* are owned by this user ID.

The following example shows how to change ownership:

Example:

```
chown -R <Server UserID>:<Server GroupID> /etc/wbem
chown -R <Server UserID>:<Server GroupID> /var/wbem
```

Customizing the CIM server startup

There are two ways to start the CIM server:

- either from the started task procedure CFZCIM (recommended)
- or from a UNIX System Services shell.

If you want to start the CIM server as started task,

- Customize the JCL procedure CFZCIM and the according environment variable file */etc/wbem/cimserver.env*.
“Customizing the started task procedure CFZCIM” describes how to perform these steps.

If you want to start the CIM server from a UNIX System Services shell or a remote UNIX session (telnet, SSH),

- Customize the UNIX System Services shell
(see “Customizing the UNIX System Services shell” on page 50)
- Set the environment variable `_BPX_JOBNAME` to CFZCIM

Customizing the started task procedure CFZCIM

You can start the CIM server via started task procedure CFZCIM. A sample of CFZCIM is shipped with the default PROCLIB.

To customize CFZCIM,

- Include CFZCIM in your PROCLIB concatenation.
- When you use the default installation directory */usr/lpp/wbem*, you need not modify CFZCIM or *cimserver.env*. Else, you need to customize the procedure in the DD statements and also update the *cimserver.env* file installed in */etc/wbem* to match the correct installation paths for the CIM server.
- The DDNAMEs `STDOUT` and `STDERR` in path */var/wbem/logs* are used to redirect the output from the console into the UNIX file system files *cimserver.out* and *cimserver.err*. When the started task is ended, job steps two and three copy the console output to the JCL job log.
- The DDNAME `STDENV` points to the hierarchical file system file containing environment variables required to run the CIM server. For running the CIM server as a started task, the environment variables are set in file *cimserver.env* located in the */etc/wbem* hierarchical file system directory. See “Setting the CIM server environment variables” on page 51 for details on how to set environment variables for the z/OS CIM server.
- To run the CIM server with a user ID for which the security setup has been completed, either set up the `STARTED` class or use the started procedures table (ICHRIN03).

For further details refer to *z/OS Security Server RACF Security Administrator's Guide*, chapter "Assigning RACF User IDs to Started Procedures".

Example of the RACF commands required to set up the CIM server for the STARTED class:

Example:

```
SETOPTS RACLIST(STARTED)
RDEFINE STARTED CFZCIM.* STDATA(USER(CFZSRV) GROUP(CFZSRVGP))
SETOPTS RACLIST(STARTED) REFRESH
```

Customizing the UNIX System Services shell

You need to customize the UNIX System Services shell, not only if you want to start the CIM server from here.

All commands of the z/OS CIM server are UNIX style programs running in a UNIX System Services shell and executing in the Enhanced ASCII mode. This means that all string data is represented in ASCII rather than in EBCDIC encoding. To be able to execute z/OS CIM server commands, a UNIX System services shell has to be started and the environment has to be set up to enable automated ASCII-EBCDIC translation and to find the necessary libraries and executables.

There are two ways to set up a shell for CIM server commands:

- In the UNIX System Services, or
- Using BPXBATCH in a JCL job

Setting up a shell in the UNIX System Services:

The file `/usr/lpp/wbem/install/profile.add` contains the basic settings to enable z/OS CIM server commands. You can add the contents of `profile.add` to `/etc/profile` to set up the z/OS CIM server environment for all users of the UNIX System Services shell or to the individual profile in the home path of each user who wants to use the commands.

Setting up a shell using BPXBATCH in a JCL job:

Use the utility BPXBATCH to run CIM server commands using a JCL job.

Example to run the cimivp utility:

```
//STEP1 EXEC PGM=BPXBATCH,TIME=NOLIMIT,REGION=0M,
//      PARM='PGM /usr/lpp/wbem/bin/cimivp 127.0.0.1'
//STDENV DD PATH='/etc/wbem/cimserver.env'
//STDOUT DD SYSOUT=*
//STDERR DD SYSOUT=*
//CEEDUMP DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSUDUMP DD SYSOUT=*
//SYSMDUMP DD SYSOUT=*
```

The file `/etc/wbem/cimserver.env` contains the basic settings for the BPXBATCH environment. You can find an alternative example for the usage of BPXBATCH in job CFZRCUST in `SYS1.SAMPLIB`.

More information:

See "Setting the CIM server environment variables" on page 51 for details on CIM server specific environment variables.

See *z/OS UNIX System Services User's Guide* for details on the BPXBATCH utility.

Setting the CIM server environment variables

Environment variables are set in file `cimserver.env`, if the CIM server runs as started task. If you use the CIM server from the UNIX System Services command prompt, the environment variables are set in UNIX System Services `.profile` in the home path of the user ID which starts the CIM server.

Setting the trace variables is not required for normal operation.

Note that changes to the environment variables become effective only after a restart of the CIM server.

The environment variable file `cimserver.env` is located in the hierarchical file system at `/etc/wbem/`. After installation, you can still find the originally shipped version in `/usr/lpp/wbem/`.

Set the following environment variables contained in this file to start the CIM server:

PEGASUS_HOME

Must be set to the hierarchical file system directory where the CIM server is installed. By default this is `/usr/lpp/wbem`.

LIBPATH

Must include the CIM server's lib and provider hierarchical file system directory paths. By default this is set to

`/usr/lpp/wbem/lib:/usr/lpp/wbem/provider:/usr/lib`

OSBASE_TRACE

Defines the trace level for the z/OS OS management CIM instrumentation. Valid values range from 0 through 4, where 4 provides the most details.

OSBASE_TRACE_FILE

Defines the filename for the z/OS CIM instrumentation traces.

PATH Only for running the CIM server or any of the CIM server command-line utilities in UNIX System Services. Must include the CIM server's bin hierarchical file system directory path so that the CIM server's executable programs are automatically found when you enter the according command at the UNIX System Services command prompt. By default this is set to `/usr/lpp/wbem/bin`.

The following variables starting with `RMF_` only apply when RMF is installed and you use the RMF monitoring providers:

RMF_CIM_PROVIDER

Used to control the behavior of the RMF CIM providers when RMF is installed. By default, the RMF CIM provider is enabled. To disable the RMF CIM provider, set the environment variable `RMF_CIM_PROVIDER=DISABLE`.

RMF_CIM_HOST

Defines the target TCP/IP address or hostname of the z/OS MVS image on which the DDS responsible for this system is running. Beginning with z/OS 1.11 the use of this environment variable is no longer required, but it will be used if defined. If omitted, the CIM monitoring providers can

automatically locate an active RMF DDS in the sysplex, provided all systems in the sysplex run z/OS 1.10 or higher.

RMF_CIM_PORT

Defines the TCP/IP port number of the DDS (default: 8803). Starting with z/OS 1.11 no longer required, but used when defined.

RMF_CIM_TRACE

Defines the trace level of the RMF CIM provider. Valid values range from 0 through 4, with 0 providing no trace and 4 providing all information possible.

RMF_CIM_TRACE_FILE

Defines the file name for storing the trace data for the z/OS RMF CIM instrumentation.

RMF_CIM_BENCH

Is used for performance benchmarks, for example, to identify the response time of the underlying RMF infrastructure. If this variable is set to 1, the RMF CIM provider will print some benchmarking information about various RMF operations, suitable for RMF development.

RMF_INDICATION_RESTTIME

Specifies the time in seconds that a provider should sleep after checking an indication subscription and before checking the next one, in order to reduce system load. The default is one second.

RMF_INDICATION_POLLING_INTERVAL

Specifies the time interval in which every single subscription is checked at most once. The default is 100 seconds.

The following variables starting with WLM_ only apply when Workload Manager (WLM) is installed and you use the WLM providers:

WLM_CIMPROVIDER_TRACE_FILE

Defines the output file name for z/OS WLM provider traces. The default trace file is /var/wlmptraces.trc.

WLM_CIMPROVIDER_TRACE_LEVEL

Defines the trace level for the z/OS WLM provider. Valid values range from 0 through 5, where 5 provides the most details. The default is 0, meaning that no trace is written.

Selecting a WLM service class for z/OS CIM priority

If you plan to use the z/OS CIM server as part of your monitoring or management infrastructure, it should run at a priority higher than the work to be managed. You should classify the CIM server into a single period service class with a velocity goal at an appropriate importance level.

Chapter 9. CIM server configuration

Configuration properties are used to control the behavior of the CIM server. The default configuration setting for the CIM server works for the majority of environments. Table 5 describes the configuration properties.

You can display or change the configuration settings using

- the `cimconfig` UNIX System Services command
- or the `MODIFY` console command

Column "dynamic Y/N" indicates if a configuration property is dynamic or not.

- Dynamic configuration properties can be changed while the CIM server is running.
- For those properties which you cannot dynamically change, use
 - either the `-p` parameter of the `cimconfig` command,
 - or the `PLANNED` option of the `MODIFY` command.

to indicate your change. Then stop and restart the CIM server.

More information:

“`cimconfig`” on page 79

“`MODIFY` console command” on page 113

“Changing current configuration properties” on page 63

“Changing planned configuration properties” on page 63

Table 5. CIM server configuration properties

Property name	Description	Default value	dynamic Y/N
<code>daemon</code>	The foreground/background process property. Set <i>daemon</i> to 'false' to run the CIM server as foreground process or as a started task.	true For running the CIM server as a started task, this option is set to 'false'.	N
<code>enableAuditLog</code>	When this option is set to true, the CIM server is writing SMF records 86. For details see “Audit logging with SMF record 86” on page 69.	false	Y
<code>enableHttpConnection</code>	The HTTP connection to the CIM server. Enables and disables connections to the CIM server over HTTP. When turned off only local connections are accepted.	true	N

Table 5. CIM server configuration properties (continued)

Property name	Description	Default value	dynamic Y/N
enableHttpsConnection	The HTTPS connection to the CIM server. Enables and disables secure connections to the CIM server via HTTPS. Note that it is not sufficient to turn on this option, but you must also enable an SSL connection through the AT-TLS feature at the z/OS Communications Server as described in “Configuring the CIM server HTTPS connection using AT-TLS” on page 29. Note: When set to true, ensure that the configured <i>httpsPort</i> can be used by the CIM server.	false	N
enableIndicationService	'true' means the indication service is enabled. 'false' will disable the indication service.	true	N
enableRemotePrivilegedUserAccess	The remote privilege for users. Enables and disables remote access for users with UID 0.	false	N
forceProviderProcesses	When this option is set to 'true', providers will run in one or more separate address spaces. For details see “Running providers in separate address spaces” on page 62. This option is ignored when MLS support is activated. The out-of-process provider support uses then one address space per security label for full protection of classified documents and information.	false	N
httpPort	The port to listen for HTTP requests. It is recommended not to change this value. Note: Make sure that the configured <i>httpPort</i> can be used by the CIM server.	5988	N
httpsPort	The port to listen for HTTPS requests. AT-TLS should be configured to use this port. It is not recommended to change this value. This value is only active if <i>enableHttpsConnection</i> is set to true. Note: Make sure that the configured <i>httpsPort</i> can be used by the CIM server.	5989	N
idleConnectionTimeout	The timeout value in seconds that the CIM server uses to wait for idle client connections to close. A client connection is considered as idle when it is not in the process of sending a request and when the CIM server is not processing a request from that connection. If the value is set to 0, no timeout is used.	0	Y
logLevel	The detail level for logging. Possible values are INFORMATION, WARNING, SEVERE, FATAL, or TRACE (see also “Logging” on page 67).	INFORMATION	Y

Table 5. CIM server configuration properties (continued)

Property name	Description	Default value	dynamic Y/N
maxFailedProviderModuleRestarts	<p>The number of times a failed provider module with indications enabled is restarted automatically before it is moved to the state Degraded.</p> <p>If this value is zero, the failed provider module is moved to the state Degraded immediately.</p>	3	Y
maxProviderProcesses	The maximum number of separate address spaces for running providers. Only in effect if <i>forceProviderProcesses</i> is set to TRUE. If the value is set to 0, the number is unlimited.	0	Y
messageDir	The message bundle directory. Do not change the default.	msg	N
providerDir	<p>The name of the directory where the provider libraries reside. You can specify multiple directories here, separated by a colon (':'). Provide the full path for all directories when changing the default.</p> <p>Since the CIM server has its own set of providers, its lib directory always needs to be present in the list of provider directories. When adding new provider directories, it is also recommended to update the LIBPATH environment variable according to the new values of providerDir. This is required, because a provider may need other supplemental dynamic load libraries, which the CIM server is not aware of and therefore would otherwise fail to load.</p>	lib:provider	Y
repositoryDir	The name of the directory for the repository.	/var/wbem/ repository	N
repositoryIs DefaultInstanceProvider	The CIM server repository serves as the default provider for CIM instances when no dynamic provider has been registered for a CIM class.	true	N
shutdownTimeout	The timeout value in seconds that the CIM server uses to wait for the shutdown process to complete. This value includes terminating active providers.	30	Y
slp	The CIM server uses the SLP Protocol to announce itself over the network.	false	N
socketWriteTimeout	The timeout value in seconds that the CIM server uses to wait for a client to receive data from the socket. After the timeout the CIM server will close the socket.	20	Y

Table 5. CIM server configuration properties (continued)

Property name	Description	Default value	dynamic Y/N
traceComponents	<p>This option specifies the component(s) that you want to trace. The value ALL enables tracing for all components.</p> <p>For more information refer to section “Tracing” on page 64, which also lists the valid components.</p>	ALL	Y
traceFacility	<p>This option specifies the trace destination.</p> <p>FILE saves the tracing messages to the file specified in <i>traceFilePath</i></p> <p>LOG saves the tracing messages to the logging facility, if <i>logLevel</i> is set to TRACE (see “Logging” on page 67). This alternative combines the tracing message stream with the log messages.</p> <p>MEMORY saves tracing messages in a wrap around memory buffer. This buffer is included in memory dumps.</p> <p>Specify the size of the allocated memory with the <i>traceMemoryBufferKbytes</i> property.</p>	Memory	Y
traceFilePath	This property specifies the fully qualified file which saves the trace data.	/tmp/cimserver.trc	Y
traceLevel	<p>Switches tracing on or off, and sets the trace level of detail. Choose one of the following trace levels:</p> <p>0 Tracing is off</p> <p>1 Severe errors</p> <p>2 Warning level error messages</p> <p>3 Inter-function logic flow, medium data detail</p> <p>4 High data detail</p> <p>5 High data detail, method enter and exit</p> <p>Note: This does not include tracing for the providers. See also “Tracing” on page 64.</p>	2	Y
traceMemoryBufferKbytes	<p>Specifies the size of the memory area which is reserved for tracing messages in kB (1kB=1024B). The value must be at least 16.</p> <p>This value only becomes valid when <i>traceFacility</i>=MEMORY.</p>	10240	N

Chapter 10. Setup verification

After performing the customization actions, you can start the CIM server as described in “Step 4: Starting the CIM server” on page 21 and run the sample application CIMIVP delivered with the product as an installation verification program.

The client application CIMIVP is delivered as executable with the product in file /usr/lpp/wbem/bin/cimivp. It displays some of the information about the z/OS system which is available through CIM.

You invoke this program as job CFZIVP contained in SYS1.SAMPLIB or from the UNIX System Services command line as cimivp.

On successful completion, it generates an output similar to the one shown hereafter.

```
cimivp Main started ...
Connecting to local CIM Server ...
... success
> Found Computer System : BOEPEG4.boeblingen.de.ibm.com
  (CPUID: 0C0B822097, VMGuestID: PEG4)
> Found Operating System : PEG4 (Version: 01.12.00,
  Sysplex: PEG4PLEX, FreeMem: 1303824)
> Number of active UNIX System Services processes: 17
> Number of active address spaces: 110
> Number of FC ports: 20
> Number of online processors: CP(3) zAAP(0) zIIP(1)
> Number of online disk volumes: 80
cimivp - All tests completed successfully.
```

If the execution of cimivp times out, this may be caused by a slow IP hostname resolution or a large amount of managed resources, like for example disks. To override the default timeout, you can set the environment variable CIM_IVP_TIMEOUT to the amount of seconds that cimivp should wait for a response from the CIM server before it fails with a timeout. When you run cimivp by submitting the CIMIVP sample job, you can add the CIM_IVP_TIMEOUT variable to file /etc/wbem/cimserver.env like this:

```
CIM_IVP_TIMEOUT=300
```

This sets the timeout for cimivp to 5 minutes.

Part 3. Administration and operation

Chapter 11. CIM server administration

While you must set up the CIM server only once to make it ready to use, you can configure your CIM server environment as often as you want during operation to best meet your requirements. The CIM server provides the ability to set a number of configuration options. Many tasks and operations for the CIM server are performed under z/OS UNIX System Services, ideally within a telnet session.

More information:

- To configure the CIM server, you can use the commands described in Chapter 12, “CIM server command-line utilities and console commands,” on page 75.
- To use the command line tools, be sure that you have set up the UNIX System Services environment as described in “Customizing the UNIX System Services shell” on page 50.
- If you run into problems while setting up or using the CIM server you can find information for problem solving in “Appendix A. Troubleshooting” on page 323.

Starting and stopping the CIM server

Start the CIM server either as a started task or from the UNIX System Services command prompt, as described in the following sections.

Running the CIM server as started task

The standard way to start the CIM server on z/OS is through the started task CFZCIM.

Before the first start:

- Make sure that you have customized the procedure CFZCIM and `cimserver.env` before you start the CIM server for the first time as described in “Customizing the started task procedure CFZCIM” on page 49 and “Setting the CIM server environment variables” on page 51.

Starting the CIM server:

- Enter the following command from the z/OS console:
`S(TART) CFZCIM`

Verifying a successful start:

- After a successful start of the CIM server, the following message is shown on the console and issued to the syslog:
`CFZ10030I: Started CIM server version 2.11 for z/OS.`

Stopping the CIM server:

- When the CIM server was started through CFZCIM, you can also stop it from the console by entering
`(STO)P CFZCIM`

Running the CIM server from the UNIX System Services command prompt

Before the first start:

- Make sure you have completed the configuration steps described in “Customizing the UNIX System Services shell” on page 50.
- Ensure that you have set the environment variable `_BPX_SHAREAS` to `NO` in your z/OS UNIX System Services shell to run the CIM server runtime environment in its own address space.

Starting the CIM server:

- Type the `cimserver` command at the command prompt of a z/OS UNIX System Services shell.

Verifying a successful start:

- After a successful start of the CIM server, the following message is shown on the console and issued to the syslog:
CFZ10030I: Started CIM server version 2.11 for z/OS.

Stopping the CIM server:

- At the command line, enter: `cimserver -s`

Running providers in separate address spaces

In a conventional CIM server setup, all providers are processed in the CIM server's address space. Only when the CIM server is running in a *multi level secured (MLS)* z/OS system, providers are executed in several provider agent processes depending on the user's security classification and port of entry, independent of the CIM server configuration.

If the CIM server is not running in an MLS system, you may want to run CIM providers in separate processes to protect the CIM server from failing CIM providers or to protect the CIM providers from each other. Rather than loading and calling CIM provider libraries directly within the CIM server process one or more provider agent processes are then started that will run the CIM provider code. In this case you can enable the *out-of-process support (OOP)* for providers. This is an enhanced version of the OpenPegasus out-of-process provider feature

To turn on out-of-process support,

- Set the configuration property `forceProviderProcesses` to `true`.
(See “Changing planned configuration properties” on page 63)

If the Enhanced Security model is enabled (that is, the CIM server is not privileged),

- Grant the CIM server user ID `READ` access to the profile `BPX.JOBNAME` defined in the `FACILITY` class.
This allows the CIM server to set the job name of the out-of-process agent to `CFZOOPA`.

Example for the security product RACF:

```
RDEFINE FACILITY BPX.JOBNAME UACC(NONE)
PERMIT BPX.JOBNAME CL(FACILITY) ACCESS(READ) ID(CFZSRV)
SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY) REFRESH
```

where CFZSRV is the CIM server user ID.

When the out-of-process support is enabled, the z/OS-specific provider property *ShareAS* and the property *ModuleGroupName* for class *PG_ProviderModule* are used. These properties specify whether a provider should run in its own address space, optionally grouped with other providers, or should be processed in the CIM server address space. They are set during provider registration via the registration MOF file. *ModuleGroupName* can also be set dynamically at runtime using the *-g* option of the *cimprovider* command.

Changing current configuration properties

You can update the current configuration while the CIM server is running for dynamic properties.

Use the *cimconfig* UNIX System Services shell command or the *MODIFY* console command to dynamically change the current configuration properties of the CIM server.

Using the *cimconfig* command without the *-p* option or the *MODIFY* console command without the *PLANNED* option results in a non-permanent change. With a restart of the CIM server these changes are reset to the planned configuration values. For making permanent changes, change the planned configuration values.

More information:

Chapter 9, “CIM server configuration,” on page 53

“*cimconfig*” on page 79

“*MODIFY* console command” on page 113

Changing planned configuration properties

To change the values of the planned configuration properties - these are the permanent values of configuration properties which are used at the CIM server startup - use

- the *cimconfig* UNIX System Services shell command with the *-p* option or
- the *MODIFY* console command with the *PLANNED* option.

The use of the *cimconfig* command is independent of whether the CIM server is running or stopped. If you change the planned configuration properties while the CIM server is running, those changes do not take effect until the CIM server is restarted. Then the planned configuration properties become the current configuration properties.

In order to use the *MODIFY* console command, the CIM server must be running. When you use the *MODIFY* console command with the *PLANNED* option, your changes do not take effect until the CIM server is restarted. Then the planned configuration properties become the current configuration properties.

More information:

- Chapter 9, “CIM server configuration,” on page 53
- “cimconfig” on page 79
- “MODIFY console command” on page 113

Tracing

To enable or to modify tracing

use the `cimconfig` command or the `MODIFY` console command. You can modify the tracing configuration properties while the CIM server is running.

See also “`cimconfig`” on page 79 and “`MODIFY` console command” on page 113.

You can modify the following tracing configuration properties:

traceLevel

turns tracing on and off and specifies the trace level. You can choose among the following trace levels:

0	Tracing is off
1	Severe errors
2	Warning level error messages (default)
3	Inter-function logic flow, medium data detail
4	High data detail
5	High data detail, method enter and exit

traceComponents

specifies the components that you want to trace.

You can choose one or more of the following components, separated by comma:

All	Authentication
Authorization	BinaryMessageHandler
CIMExportRequestDispatcher	CIMOMHandle
CMPIProvider	CMPIProviderInterface
Config	ControlProvider
CQL	DiscardedData
Dispatcher	ExportClient
Http	IndicationFormatter
IndicationGeneration	IndicationHandler
IndicationReceipt	IndicationService
IPC	L10N
Listener	LogMessages
MessageQueueService	ObjectResolution
OsAbstraction	ProviderAgent
ProviderManager	Repository
Server	Shutdown
SSL	StatisticalData
Thread	UserManager
WsmServer	WQL
Xml	XmlIO

The following components have a special purpose:

Special purpose trace components	Description
All	Traces all available components
DiscardedData	Issues a trace message when information is discarded or an operation is cancelled
LogMessages	Traces all messages written to the logging facility
StatisticalData	Prints statistical data to the trace at level 4
XmlIO	Prints the complete CIM-XML messages

traceFacility

specifies the destination of the trace messages.

FILE

saves the trace messages to the file specified in *traceFilePath*.

This file is continuously growing. You can remove it while the CIM server is running. It will be recreated automatically.

LOG

saves the trace messages to the logging facility, if the *logLevel* is set to TRACE (see “Logging” on page 67). This alternative combines the log messages and the trace messages to one message stream.

MEMORY

saves trace messages in a wrap around memory buffer. This buffer is included in memory dumps. (default).

To find the trace in a memory dump, the top of the allocated memory block is flagged with "PEGASUSMEMTRACE". The last trace message is flagged with the suffix "EOTRACE". The flags are encoded in ASCII.

Specify the size of the memory buffer with the static *traceMemoryBufferKbytes* property.

traceFilePath

if *traceFacility*=FILE, this property specifies the file which saves the trace data. The default is /tmp/cimserver.trc.

traceMemoryBufferKbytes

specifies the size of the memory area which is reserved for trace messages in kB (1kB=1024B). The default is 10240. The value must be at least 16. *traceMemoryBufferKbytes* is a planned configuration property (see “Changing planned configuration properties” on page 63).

This area is allocated when *traceFacility*=MEMORY.

Tracing providers running out-of-process:

When tracing is enabled in the CIM server, it is also enabled in the provider agent processes. For reasons of trace data integrity and regarding performance aspects, a separate trace file is used for each provider agent process.

Each provider agent is uniquely identified by the name of the shared provider agent executable. Each non-shared instance of a provider agent corresponds with a single provider module. This name is used as an extension to the trace file name specified by the *traceFilePath* configuration property. For example, if *traceFilePath* is defined as */tmp/cimserver.trc*, the non-shared provider agent for the *OperatingSystemModule* would direct its trace output to the file */tmp/cimserver.trc.OperatingSystemModule*.

Examples:

To set the trace level to trace all information with high data detail in the *Thread* and *ProviderManager* components,

type the following commands into the UNIX System Services shell:

```
cimconfig -s traceLevel=4
cimconfig -s traceComponents=Thread,ProviderManager
```

or

```
F CFZCIM,APPL=CONFIG,traceLevel=4
F CFZCIM,APPL=CONFIG,traceComponents='Thread,ProviderManager'
```

on the console.

To disable all tracing,

type the following command into the UNIX System Services shell:

```
cimconfig -s traceLevel=0
```

To route both trace and log messages to a file:

type the following commands into the UNIX System Services shell:

```
cimconfig -s traceLevel=1
cimconfig -s traceComponents=Thread,ProviderManager,LogMessages
cimconfig -s traceFacility=FILE
cimconfig -s traceFilePath=/tmp/cimserver1.trc
```

The CIM server now saves severe trace messages in the *Thread* and *ProviderManager* components and all log messages to the file */tmp/cimserver1.trc*.

To route both trace and log messages to memory:

type the following commands into the UNIX System Services shell:

```
cimconfig -s traceLevel=1
cimconfig -s traceComponents=Thread,ProviderManager,LogMessages
cimconfig -s traceFacility=MEMORY
```

The CIM server now saves severe trace messages in the *Thread* and *ProviderManager* components and all log messages to the default memory space of 10240kB.

To route both trace and log messages to the z/OS Communications Server's system logger (syslog) daemon:

1. configure the syslog daemon as described in z/OS *Communications Server: IP Configuration Reference* and z/OS *Communications Server: IP Configuration Guide*
2. type the following commands into the UNIX System Services shell:

```
cimconfig -s logLevel=TRACE
cimconfig -s traceLevel=1
cimconfig -s traceComponents=Thread,ProviderManager
cimconfig -s traceFacility=LOG
```

The CIM server now writes severe trace messages in the *Thread* and *ProviderManager* components and all log messages to the syslog daemon.

See also “Logging.”

Logging

The CIM server sends log messages

- to the z/OS *system console*,
- to *stderr*,
- if the CIM server is run as a started task. The logs are captured in */var/wbem/logs/cimserver.err*.
- to the z/OS *Communications Server's system logger (syslog) daemon*,
if the syslog daemon is configured as described in *z/OS Communications Server: IP Configuration Reference* and *z/OS Communications Server: IP Configuration Guide*,
- and to the *trace facility*,
if *traceComponents* includes the element *LogMessages*, (see also “Tracing” on page 64).

Generally logging for the CIM server is enabled and cannot be turned off. However, you can configure the level of logging.

To modify the log level

use the *cimconfig* command or the *MODIFY* console command to change the *logLevel* configuration property.

Examples

- type the following command into the UNIX System Services shell while the CIM server is running:
`cimconfig -s logLevel=INFORMATION`
- or type the following command into the z/OS system console:
`F CFZCIM,APPL=CONFIG,logLevel=INFORMATION`

See also “*cimconfig*” on page 79 and “*MODIFY* console command” on page 113.

Log levels

You can choose between five different log levels:

INFORMATION (default)

The default setting for *logLevel* is *INFORMATION*. This setting should not be changed unless there is a specific need for a more or less detailed logging.

WARNING

returns log messages for warnings, severe and fatal errors

SEVERE returns log messages for severe and fatal errors

FATAL returns log messages only for fatal errors

TRACE returns all log messages and all trace messages

trace messages are only routed to the z/OS Communications Server's system logger (syslog) daemon - never to the system

console. Remember to set *traceFacility* to LOG, otherwise no trace message is displayed in the syslog daemon (see “Tracing” on page 64).

Using the syslog daemon for CIM server logging

The z/OS CIM server will connect to the syslog daemon and send all of its log messages to it, where the filtering according to the *logLevel* configuration property applies as described above. Therefore no messages will be submitted to the syslog daemon which have a higher log level than what’s specified in the current value of the *logLevel* configuration property.

Messages that go to the syslog daemon are prepended with an according z/OS message number, which is either one of the generic CFZ00001E, CFZ00002W or CFZ00004I messages followed by a PGSxxxxx message number, or one of the directly mapped z/OS specific CFZxxxxx message numbers.

Syslog messages from the z/OS CIM server will have an identifier of “CFZCIM” and also contain the CIM server's process ID.

The log levels of the z/OS CIM server are mapped to the following syslog levels:

Table 6. Log and syslog levels

Log level	Syslog level
INFORMATION	LOG_INFO
WARNING	LOG_ERR
SEVERE	LOG_WARNING
FATAL	LOG_ERR
TRACE	LOG_DEBUG

The syslog service must be properly configured for CIM, and the syslog daemon must be started as described in *z/OS Communications Server: IP Configuration Reference* and *z/OS Communications Server: IP Configuration Guide*.

Following is a sample syslog configuration file (*/etc/syslog.conf*) entry for the CIM server, which tells the syslog daemon to create log files:

Example:

```
...
*.CFZ*.*.debug /var/wbem/logs/cimserver_%Y.%m.%d.syslog
...
```

When configured like this, the CIM server log messages will be displayed in the format shown by the following example:

Example:

```
Nov  7 12:48:38 BOECFZ1 CFZCIM[33557318]:  
CFZ10025I: The CIM server is listening on HTTP port 5,988.  
Nov  7 12:48:38 BOECFZ1 CFZCIM[33557318]:  
CFZ10028I: The CIM server is listening on the local connection socket.  
Nov  7 12:48:38 BOECFZ1 CFZCIM[33557318]:  
CFZ10030I: Started CIM Server version 2.11  
Nov  7 12:48:38 BOECFZ1 CFZCIM[33557318]:  
CFZ12533I: The CIM server failed to register with ARM using  
element name CFZ_SRV_PEG2: return code 0x0C, reason code 0x0168.  
Nov  7 12:49:01 BOECFZ1 CFZCIM[33557318]: CFZ10031I: CIM Server stopped.
```

Except for the CIM server's *logLevel* property, all configuration now occurs through the syslog service as described in *z/OS Communications Server: IP Configuration Reference* and *z/OS Communications Server: IP Configuration Guide*.

Configuration of the syslog daemon for specific processes/daemons is done based on the job name of the process writing the logs.

When you run the CIM server as started task,
the job name is always CFZCIM.

When you have started the CIM server from the UNIX System Services command prompt,
the job name of the CIM server is the user ID that started the CIM server.
Be sure that you have set environment variable `_BPX_JOBNAME` to CFZCIM in order to set the job name of the CIM server correctly. Otherwise it will be difficult to create a syslog configuration for the CIM server.

Audit logging with SMF record 86

The CIM server can file audit log records to SMF record 86. These records contain information about authentication, configuration, provider status, and CIM operations. For details of SMF record 86, see *z/OS MVS System Management Facilities (SMF)*.

To enable writing audit SMF record 86, modify the SMF, the CIM server, and the security configuration:

SMF configuration:

- Ensure that record 86 is part of your active SMF configuration SMFPRMXX PARMLIB member.

CIM server configuration:

- To enable the CIM server to write audit records, set the configuration property **enableAuditLog** to true.

When recording is switched on, the current CIM server configuration and the status of the currently loaded providers is recorded. To disable recording, set the configuration property to false. This property can be changed dynamically during CIM server runtime.

Security configuration:

- In order to write SMF records, the CIM server needs at least READ access to the BPX.SMF profile of the FACILITY class at your SAF product.

Example for RACF:

```
RDEFINE FACILITY BPX.SMF UACC(NONE)
PERMIT BPX.SMF CL(FACILITY) ACCESS(READ) ID(CFZSRV)
SETROPTS RACLIST(FACILITY) REFRESH
```

If the CIM server audit logging is enabled, but SMF does not collect SMF record 86 or subtypes, or SMF is not enabled at all, no records are written.

Backing up the CIM server configuration

After you have set up and configured the z/OS CIM server, you should back up the following CIM server property configuration files located in */etc/wbem*:

`cimserver_planned.conf`

containing planned values which have been modified but are not yet in effect. They will be picked up at the next CIM server restart.

`cimserver.env`

containing the environment variables for the started task CFZCIM

How to backup the CIM server repository is described in “Backing up the CIM server repository” on page 73.

Automatically restarting the CIM server

Since the CIM server serves as a primary system management interface for a system, it should be continuously available.

To support the CIM server availability, startup and shutdown messages are logged to the z/OS console to be used with a systems management program such as IBM Tivoli® System Automation.

The z/OS CIM server is enabled for the Automatic Restart Manager (ARM). The CIM server needs no additional configuration to use ARM, it always registers itself to ARM. When ARM is active and the CIM server is authorized to register with ARM, then success message CFZ12532I is displayed in the system log. Otherwise, information message CFZ12533I is displayed in the system log to inform you that the CIM server is not registered to ARM.

You can use ARM only for started task procedures or batch jobs. So if you start the CIM server from the UNIX System Services shell, you also get the message CFZ12533I. If you do not plan to use ARM, you can ignore this message, which is issued every time when the CIM server is started.

The CIM server issues the registration and the ready request after a successful bind to the communication socket/s (HTTP, HTTPS, and/or Local). It is deregistered from ARM during its normal shutdown procedure. In all other cases, the CIM server remains registered and is restarted based on the active ARM policy.

In a sysplex, you can start only one CIM server per OS image. Therefore ARM can only be used to restart after an application ABEND and not for cross-system restarts. You must use other facilities to start the CIM server during an IPL.

More information:

ARM policy considerations

The CIM server has the following requirements for exploiting the ARM restart policy:

- The ARM element name used for the CIM server is CFZ_SRV_<system_name>, where <system_name> is substituted by the value of the system symbol SYSNAME.
- The CIM server can only be restarted on the system where it failed. A cross-system restart within a sysplex is not possible. Therefore the termination type has to be ELEMTERM.
- The restart occurs through starting the CIM server started task procedure CFZCIM.

The sample JCL CFZARMP is installed to the SYS1.SAMPLIB during SMP/E z/OS installation of the CIM component.

```

//CFZARMP JOB MSGCLASS=C,MSGLEVEL=(1,1),USER=XXXXXX,NOTIFY=XXXXXX
//*****
//*
//* PROPRIETARY STATEMENT:
//* Licensed Materials - Property of IBM
//* 5694-A01 Copyright IBM Corp. 2005, 2009
//*
//* STATUS=HPG7760
//*
//* DESCRIPTIVE NAME:
//*
//* SAMPLE JCL TO UPDATE THE ADMINISTRATIVE POLICY DATA FOR CIM
//* SERVER IN THE COUPLE DATA SET FOR ARM (AUTOMATIC RESTART MANAGER)*
//*
//* NOTES:
//*
//* 1. SYSPRINT DD IS A REQUIRED DD STATEMENT FOR THE UTILITY
//* OUTPUT.
//* 2. SYSIN DD IS A REQUIRED DD STATEMENT FOR THE UTILITY
//* CONTROL STATEMENTS.
//* 3. DATA TYPE(ARM) STATEMENT IS REQUIRED TO SPECIFY WHAT TYPE
//* OF COUPLE DATA SET IS TO BE UPDATED.
//* 4. REPORT KEYWORD IS OPTIONAL. WHEN REPORT(YES) IS SPECIFIED,
//* AN ARM ADMINISTRATIVE POLICY REPORT WILL BE GENERATED IN
//* THE OUTPUT. THE DEFAULT VALUE FOR REPORT IS YES.
//* 5. REPLACE KEYWORD IS OPTIONAL. WHEN REPLACE(YES) IS SPECIFIED
//* FOR A POLICY, THE POLICY WILL BE REPLACED IF IT ALREADY
//* EXISTED IN THE COUPLE DATA SET.
//* IF REPLACE(NO) IS SPECIFIED FOR AN EXISTING POLICY,
//* THE UPDATE JOB WILL BE FAILED AND NO CHANGES WILL BE MADE
//* TO THE COUPLE DATA SET.
//* 6. TO DELETE AN EXISTING POLICY IN A COUPLE DATA SET,
//* INCLUDE THE FOLLOWING LINE IN THE SYSIN DD CARD:
//* DELETE POLICY NAME(CFZARMP0)
//* WHERE POLNAME IS THE NAME OF THE POLICY TO BE DELETED.
//*
//*****
//STEP1 EXEC PGM=IXCMIAPU
//STEPLIB DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=A
//SYSABEND DD SYSOUT=A
//SYSIN DD *

DATA TYPE(ARM)
REPORT(YES)

DEFINE POLICY NAME(CFZARMP0) REPLACE(YES)

RESTART_GROUP(CFZCIMRESGRP)
/* List all systems where the CIM Server can be started */
TARGET_SYSTEM(SYS1)
/* Wait 10 sec before restarting to free resources */
RESTART_PACING(10)

ELEMENT(CFZ_SRV_*)
RESTART_ATTEMPTS(3,300)
RESTART_TIMEOUT(300)
READY_TIMEOUT(300)
/* coss-system restart is not allowed. */
/* No restart after system failure */

TERMTYPE(ELEMTERM)
RESTART_METHOD(ELEMTERM,STC,'S CFZCIM')

/*

```

Backing up the CIM server repository

The CIM server keeps definitions of the data about managed objects and their providers in its repository located in */var/wbem*.

It is important to schedule backups of the repository directories and files. If the repository is deleted or corrupted, backups of the repository files need to be restored. If the repository files cannot be restored from a backup, refer to section “Migration from z/OS 1.11 or z/OS 1.12 to z/OS 1.13” on page 18 for information about how to recover the repository.

As recommended in the *z/OS Program Directory*, the path */var/wbem* should be mounted as a separate data set to simplify backing up. It is also recommended to stop the CIM server during backup to avoid data corruption.

Note: If the repository was backed up from a prior z/OS release, it should not be restored onto a system that runs a later version of z/OS. Once a new version of z/OS was installed and the CIM server has been initially started, you should immediately back up the upgraded repository and discard old repository backups.

Chapter 12. CIM server command-line utilities and console commands

The CIM server includes a set of command-line utilities and console commands that you can use to control or change the CIM server environment or to send CIM requests to CIM servers on z/OS or non-z/OS systems. You run most of the command-line utilities from a z/OS UNIX System Services shell.

Prepare the UNIX System Services shell as follows:

- Be sure that your environment is set up as described in
 - “Step 5: Customizing the UNIX System Services shell” on page 21 or
 - “Customizing the UNIX System Services shell” on page 50
- Grant system administrators using the command-line utilities CONTROL access to profile CIMSERV in class WBEM

CIM server utilities and commands:

cimmof These commands are used to compile provider registrations and to compile CIM class descriptions written in the managed object format (MOF) language. The compiled information is put into the class schema stored in the repository.

The cimmof command is described in “cimmof” on page 77.

cimconfig

This command configures the options for the CIM server. Depending on the property being configured, the CIM server may need to be restarted after using this command.

The cimconfig command is described in “cimconfig” on page 79.

cimprovider

This command can be used to control the registered providers. The CIM server must be running to use this command.

The cimprovider command is described in “cimprovider” on page 81.

cimcli This command lets you perform CIM client requests/operations against the local or remote CIM servers. It implements most of the DMTF CIM operations.

Each call of cimcli invokes a CIM operation with the corresponding parameters equivalent to the CIM operations defined in the *CIM Operations over HTTP* specification. Additionally, the cimcli command-line interface implements a number of other specific operations that support testing and querying CIM servers, including operations to query for namespaces and to get all instances in a namespace.

The cimcli command is described in “cimcli” on page 84.

cimsub This command lets you manage CIM indications on the local CIM server. The command can list, enable, disable and remove indication subscriptions, filters and handlers.

The cimsub command is described in “cimsub” on page 110.

MODIFY console command

Like the `cimconfig` command, the `MODIFY` console command configures the options for the CIM server while the CIM server is running. Depending on the property being configured, the CIM server may need to be restarted after using this command.

The `MODIFY` console command is described in “`MODIFY` console command” on page 113.

Note: The `wbemexec` utility is also included with CIM. It is used to directly send CIM-XML requests to a CIM server. However, this tool is not supported, but just supplied on an 'as-is-base'.

You can specify most options provided by the utilities in two ways:

- a short form introduced by a single dash, for example `-f<file>`
- a long form introduced by a double dash, for example `--file=<file>`

To understand the syntax of the description of the command-line utilities, see “How to read syntax diagrams” on page 347.

cimmof

Purpose


These commands are used to compile provider registrations or to compile CIM class descriptions written in the MOF language and store the information in the repository. For `cimmof`, the CIM server must be started before using this command.

The CIM server MOF compiler is a command-line utility that compiles MOF files (using the MOF format defined by the DMTF CIM Specification) into a CIM server repository. It allows compiling from structures of MOF files using the `include #pragma` and can either compile into a CIM server repository or check the syntax of the MOF files. The compiler requires that the input MOF files are in the current directory or that a fully qualified path is given. MOF files that are included using the `include #pragma` must be in the current directory or in a directory specified by a `-I` command-line switch.


For using the `cimmof` command against the CIM server namespaces (`root/PG_Internal`, `root/PG_InterOp`), a user needs to have `CONTROL` access to profile `CIMSERV` in class `WBEM`.

Syntax

Main diagram:



Options:



Options

mof_file

Specifies the MOF file or MOF files to compile.

--version

Displays the CIM server version.

- h, -help, or no specified option**
Prints out a usage message with command definitions.
- I *path*** Specifies a path to the included MOF files.
- n *path*, --namespace=*path***
Overrides the default CIM repository namespace path. The default is root/cimv2.
- xml** Generates XML to standard output. This option does not update the repository.
- trace, --trace=*filename***
Writes trace information to a file. If *filename* is omitted, the output destination is standard output. Those files are written with ASCII encoding.
- E** Performs a syntax check on the input. This option does not update the repository.
- w** Suppresses warning messages.
- uc** Allows the update of an existing class definition. This option lets you update a leaf class. It does not allow updates of superclasses or classes that have subclasses.
- aE** Allows the addition or modification of classes with the experimental qualifier.
- aV** Updates a class that results in a version change. The version must be specified in a valid format. The format is *m.n.u* where *m* is major version, *n* is minor release and *u* is update. For example, 2.7.0 is a valid format for CIM Schema 2.7.0. If the input class has the same version as the class in the repository, the class is not updated.
- aEV** Allows both Experimental and Version Schema changes.

Examples

cimmof -w -I./myDir myDir/CIM_Schema211.mof

In this example, the managed object format (MOF) file that is located in directory *myDir* with the name *CIM_Schema211.mof* is compiled into the default namespace *root/cimv2*. *CIM_Schema211.mof* includes #pragmas for other MOF files that are also in the *myDir* directory. Therefore an include (-I) option is required for the *myDir* directory. The -w option suppresses warning messages.

cimconfig

Purpose

Use the `cimconfig` command to manage CIM server configuration properties. You can get, set, unset, or list these properties. See Chapter 11, “CIM server administration,” on page 61 for more information.

You can use the `cimconfig` command to set the current or planned configuration properties of the CIM server.

Current configuration properties:


You can update the current configuration properties only while the CIM server is running. After a restart of the CIM server, these changes will be reset to the planned or default configuration values. For making permanent changes, you must change the planned configuration values.

Planned configuration properties:

Planned configuration properties can be modified even if the CIM server is stopped. If the planned configuration properties are changed when the CIM server is running, those changes do not take effect until the CIM server is restarted.

For using the `cimconfig` command, a user needs to have `CONTROL` access to profile `CIMSERV` in class `WBEM`.

Syntax



Options

The `cimconfig` command recognizes the following options:

-g *property-name*, -g *property-name* -c

Gets the current value of the configuration property *property-name*. Returns an error when the CIM server is not running.

-g *property-name* -p

Gets the planned value of the configuration property *property-name*.

-g *property-name* -d

Gets the default value of the configuration property *property-name*. Returns an error when the CIM server is not running.

-s *property-name*=*value*, -s *property-name*=*value* -c

Sets the current configuration property *property-name* to the value *value*. Returns an error when the CIM server is not running or the specified property cannot be updated dynamically.

- s *property-name=value* -p**
Sets the planned configuration property *property-name* to the value *value*.
- u *property-name*, -u *property-name* -c**
Unsets the value of the current configuration property *property-name* to its default value. Returns an error when the CIM server is not running or the specified property cannot be updated dynamically.
- u *property-name* -p**
Unsets the value of the planned configuration property *property-name* to its default value.
- l** Lists the names of all configuration properties. Returns an error when the CIM server is not running.
- l -c** Lists the name and value pairs of all current configuration properties. Returns an error when the CIM server is not running.
- l -p** Lists the name and value pairs of all planned configuration properties.
- version**
Displays the CIM server version.
- h, --help, no options specified**
Displays the command help information.

Examples

cimconfig -s traceLevel=4

cimconfig -s traceComponents=XmlIO,Http

Sets the trace level to trace all information with high data detail in the *XmlIO* and *Http* components.

cimconfig -s logLevel=WARNING -p

Sets the *logLevel* configuration property to the value `WARNING` in the *cimserver_planned.conf* file.

cimprovider

Purpose

The `cimprovider` command lets you disable, enable, remove, and list registered CIM providers or CIM provider modules and the according module status. In addition, it allows you to define groups of provider modules to be run in the same provider agent process.

disable

When a CIM provider is disabled, the CIM server rejects any requests to the provider. When a provider module is disabled, any new requests to the providers that are contained in the specified provider module are rejected.

enable

When a CIM provider is enabled, the CIM server forwards requests to the provider. When a provider module is enabled, the providers that are contained in the provider module are ready to accept a new request.

remove

When a CIM provider is removed (unregistered), the CIM server will no longer have any information about the provider. When a CIM provider module is removed (unregistered), the CIM server will no longer have any information about any provider contained in the module. If you want to address requests to a provider after removal, the provider or provider module must be registered again (typically by loading its registration schema using the `cimof` command).


list

You can list all registered provider modules and the according module status or all providers in the specified provider module.

group Allows grouping of provider modules in a single provider agent process when running the CIM server in out-of-process mode, that is, configuration property `forceProviderProcesses` is true.

For using the `cimprovider` command, the CIM server must be running, and the user needs to have `CONTROL` access to profile `CIMSERV` in class `WBEM`.

Syntax



Options

The `cimprovider` command recognizes the following options:

-d -m *module-name*
 Disables the CIM provider module *module-name*. If the module is already disabled, an error message is returned.

-e -m *module-name*
 Enables the CIM provider module *module-name*. If the module is already enabled or is currently being disabled, an error message is returned.

-g *group-name* -m *module-name*
 Sets the CIM provider module group. To remove a provider module from grouping, specify an empty string. If the provider module is active, it will be disabled before the group is set and then enabled again. All provider modules with the same group name are loaded into a single agent address space. If CIMServer is specified as group name, the provider module is loaded into the CIM server address space. Provider module groups are only in effect when running the CIM server in out-of-process mode.

-r -m *module-name*
 Removes the provider module *module-name* and all of its contained providers.

-r -m *module-name* -p *provider-name*
 Removes the provider *provider-name* in the provider module *module-name* without affecting any other providers in that module.

-l
 Displays all registered provider modules.

To list all providers in all modules, type a `cimprovider -l` command, followed by `cimprovider -l -m` for each listed module.

-l -s
 Lists the status of all registered provider modules.

-l -f
 Lists the full status of all registered provider modules and their module group name.

-l -m *module-name*
 Lists all registered providers in module *module-name*.

--version
 Displays the CIM server version.

-h, --help, no *option specified*
 Displays the command help information.

Limitations

This command disables, enables, or removes one CIM provider module or CIM provider at a time.

Examples

cimprovider -d -m myProviderModule

Disables provider module myProviderModule and all of its contained providers (placing them in a stopped state).

cimprovider -e -m myProviderModule

Enables provider module myProviderModule and all of its contained providers (placing them in an OK state).

cimprovider -r -m myProviderModule

Removes (unregisters) the myProviderModule provider module and all of its contained providers.

cimprovider -r -m myProviderModule -p MyProvider

Removes (unregisters) the MyProvider provider contained in the myProviderModule provider module.

cimprovider -l

Lists the registered provider modules.

cimprovider -l -s

Lists the registered provider modules and their status (such as OK, Stopping, Stopped).

cimprovider -l -m myProviderModule

Lists the registered providers, which are in the myProviderModule provider module.

cimprovider -g myProviderGroup -m myProviderModule

Adds provider module myProviderModule to the group myProviderGroup. Module myProviderModule will be processed in the same provider agent process as all other providers in the group myProviderGroup.

Purpose

z/OS provides a command-line interface called `cimcli` through which you can perform CIM client requests/operations. It implements most of the DMTF CIM operations except for the *modifyClass*, *modifyInstance* and *createClass* operations.

Each execution of `cimcli` invokes a CIM operation with the corresponding parameters equivalent to the CIM operations defined in the *CIM Operations over HTTP* specification.

In addition to the basic CIM operations defined in this specification, the `cimcli` command-line interface implements a number of other specific operations that support testing and querying CIM servers, including operations to query for namespaces and to get all instances in a namespace.

The command-line client is invoked from the UNIX System Services shell.

Syntax

Main diagram:



Operation:

Defines the operation to be performed. `cimcli` performs all of the DMTF CIM operations (for example, `getClass`) and a set of compound operations (for example, `enumerateNamespaces`).

There are two forms for each operation: a long form which is the full name of the operation (for example, `getClass`), and a short form, typically two characters (for example, `gc` for `getClass`).

Options


-h	Prints help usage message.
-hc	Prints CIM operation command list.
--help	Prints full help message with commands, options, and examples.
-ho	Prints list of options.
--version	Displays the software version.

cimcli a (associators)

Purpose

Enumerates the classes or instances linked (associated) to a CIM class or a CIM instance.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli a IBMzOS_Process
```

Results

0 Successful execution of the operation

all values other than 0

The execution on the operation returned an error.

For a given class, the list of associated classes is returned.


For a given instance name, the list of associated instances is returned.

cimcli an (associatorNames)

Purpose

Enumerates the class or instance names linked (associated) to a CIM class or a CIM instance.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli an IBMzOS_Process
```

Results

0 Successful execution of the operation

all values other than 0

The execution on the operation returned an error.

For a given class, the list of associated class names is returned.


For a given instance name, the list of associated instance names is returned.

cimcli ci (createInstance)

Purpose

Creates one instance of the specified class with the provided properties in the repository.

Operation



Usage

The *classname* parameter defines the class for which the instance is to be created. The optional set of parameters defines the properties to be provided (see also “cimcli *Instance name*” on page 109). The command reads the specified class and inserts the properties. The command will be rejected if the class does not exist in the namespace.

Specify a *value* for a property name according to its type. Follow the syntax rules as specified in *Common Information Model Specification, DSP0004, Version 2.3* by the DMTF. Note special syntax rules to define

- the current date and time with the keyword *now* for values of the type *Datetime*
- an empty string with the property name followed by a *!* for values of the type *string*
- an *NULL* string with the property name followed by a *=* for values of the type *string*

Options

For special options and “Common options”, see “cimcli *Options*” on page 107.

Examples

```
cimcli ci CIM_Person Name=Michael Title=Engineer
```

Creates an instance of the class *CIM_Person*.

Results

The command returns the object path of the created instance if the call to the CIM server was performed. Otherwise it returns the exception received.

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli dc (deleteClass)

Purpose

Deletes the CIM class specified by *classname*.

Operation



Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli dc CIM_Person
```

Deletes the class `CIM_Person` and all sub-classes when there are no instances.

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli di (deleteInstance)

Purpose

Deletes the specified instance or interactively one instance from the specified class.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Usage

If the instance name is specified, the operation is performed directly. If a class name is specified, the enumerateInstanceNames command is performed with the class name and the list of returned instance names is presented to the user to select one to delete. cimcli then performs deleteInstance with the selected instance name.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli di CIM_Person
```

Interactively deletes an instance of class CIM_Person.

Results

0 Successful execution of the operation

all values other than 0

The execution on the operation returned an error.


There is no response if the instance was successfully deleted, or an exception returned if there were any errors.

cimcli dq (deleteQualifier)

Purpose

Deletes the CIM qualifier specified by *qualifiername*.

Operation



Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli dq ASSOCIATION
```

Deletes the qualifier Association (generally not recommended).

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli ec (enumerateClasses)

Purpose

Enumerates the classes starting at the level defined by *classname*.

Operation



Usage

If the class name is omitted, cimcli inserts an empty class name.

Options

-di enumerates all inherited classes

If you do not specify this parameter, only the child classes are enumerated.

For all other special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli ec -n root/cimv2 -niq
```

Enumerates classes from the root of the root/cimv2 namespace.

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli ei (enumerateInstances)

Purpose

Enumerates the instances of the specified CIM class.

Operation



Options

For special options and "Common options", see "*cimcli Options*" on page 107.

Examples

```
cimcli ei CIM_ComputerSystem -di
```

Enumerates the instances of class `CIM_Computersystem`, listing properties of inherited classes (`-di`).

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli eq (enumerateQualifiers)

Purpose

Enumerates all qualifiers in the specified or default namespace.

Operation



Options

For special options and "Common options", see "*cimcli Options*" on page 107.

Examples

```
cimcli eq
```

Enumerates qualifiers in the default root/cimv2 namespace.

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli gc (getClass)

Purpose

Gets the class of *classname*.

Operation



Options

For special options and "Common options", see "*cimcli Options*" on page 107.

Examples

```
cimcli gc IBMzOS_Process
```

Gets the definition for class `IBMzOS_Process`.

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli gi (getInstance)

Purpose

Displays the specified instance.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Usage

If the instance name is specified, the operation is performed directly. If a class name is specified, the enumerateInstanceNames command is performed with the class name and the list of returned instance names is presented to the user to select one to display. cimcli then performs getInstance with the selected instance name.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli gi IBMzOS_UnixLocalFileSystem
```

Interactively returns a list of instances from class IBMzOS_UnixLocalFileSystem. The user can select one instance to be displayed.

Results

0 Successful execution of the operation

all values other than 0

The execution on the operation returned an error.

If an instance is specified, the operation displays the result from the CIM server.

If a class is specified, an enumerateInstanceNames CIM operation is performed, and if any instance names are returned, the result is presented for the user to select one of the instances to be displayed.


If there are no instances, the command returns an empty response.

cimcli gq (getQualifier)

Purpose

Gets the CIM qualifier specified by *qualifiername*.

Operation



Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

`cimcli gq Association`

Gets the qualifiers in mof output format

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli im (invokeMethod)

Purpose

Performs the extrinsic method *methodname* on the specified class or instance.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Usage

The parameters are supplied as *name=value* pairs. In the current version, all parameters are treated as strings.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli im 'IBMzOS_Test.handle="1"' TriggerIndication NumberOfIndications=3
```

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli mi (modifyInstance)

Purpose

Modifies the specified instance or creates a modified instance of the specified class by building the properties from a combination of the target class and the provided properties.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli mi CIM_xxxx name=abc size=zyx
```

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli nc (enumerateClassNames)

Purpose

Enumerates sub class names of *classname* or all top level class names of a given namespace.

Operation



Usage

Note that on z/OS all class names are returned in lowercase due to a z/OS specific performance optimization. Use the `getclass` operation to receive the exact case of the class name.

Options

For special options and "Common options", see "*cimcli Options*" on page 107.

Examples

```
cimcli nc -di
```

Enumerates all class names from the root/cimv2 namespace, including subclasses (-di).

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli ni (enumerateInstanceNames)

Purpose

Enumerates all instances of the specified class.

Operation



Options

For special options and "Common options", see "*cimcli Options*" on page 107.

Examples

```
cimcli ni CIM_Processor -n root/cimv2
```

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli ns (enumerateNamespaces)

Purpose

Requests an enumeration of all the namespaces in the target CIM server. This command uses both the CIM_Namespace class and if that fails, the __Namespace class to determine the list of namespaces.

Operation



Options

For "Common options", see "*cimcli Options*" on page 107.

Examples

```
cimcli ns
```

Results

0 Successful execution of the operation

all values other than 0


The execution on the operation returned an error.

cimcli r (references)

Purpose

Enumerates the association classes or association instances linked to the specified CIM class or CIM instance.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli r 'IBMzOS_ComputerSystem.  
        CreationClassName="IBMzOS_ComputerSystem",  
        Name="sys1"'
```

```
cimcli r IBMzOS_OperatingSystem -rc CIM_OSProcess
```

Results

0 Successful execution of the operation

all values other than 0

The execution on the operation returned an error.

For a given class, the list of linked association classes is returned.


For a given instance name, the list of linked association class instances is returned.

cimcli rn (referenceNames)

Purpose

Enumerates the association class or instance names linked to the specified CIM class or CIM instance.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli rn 'IBMzOS_ComputerSystem.
          CreationClassName="IBMzOS_ComputerSystem",
          Name="sys1"'
cimcli rn IBMzOS_OperatingSystem -rc CIM_OSProcess
```

Results

0 Successful execution of the operation

all values other than 0

The execution on the operation returned an error.

For a given class, the list of linked association class names is returned.


For a given instance name, the list of linked association instance names is returned.

cimcli sp (setProperty)

Purpose

Sets a single property on a named instance.

Operation



For "Instance name", see "cimcli *Instance name*" on page 109.

Usage

If the instance name is specified, the operation is performed directly. If a class name is specified, the `enumerateInstanceNames` command is performed with the class name and the list of returned instance names is presented to the user to select one to set. `cimcli` then performs `setProperty` with the selected instance name.

Options

For special options and "Common options", see "cimcli *Options*" on page 107.

Examples

```
cimcli sp 'CIM_Person.Name="Michael"' HomePhone=123456789
```

Sets the HomePhone property to 123456789.

Results

0 Successful execution of the operation

all values other than 0

The execution on the operation returned an error.

There is no response at the command prompt when the property has been successfully set.

1

1

1

1



1
1
1
1

Options

Examples

Results

all values other than 0

The execution on the operation returned an error.


Chapter 12. CIM server command-line utilities and console commands 105

cimcli *Options*

Purpose

Options are identified on the command line with the '-' or '--' notation. An option that is not used by a particular operation is ignored.

Common options



Usage

The cimcli command recognizes the following common options:

- count** *number* Expected number of objects returned, if the **-sum** option is set. Tests this number and displays the difference. Term nonzero is returned if test fails.
- d** Displays more detailed debug messages.
- delay** *number* Delay in seconds between connection and request. Default is 0.
- l** *location* Allows input of the host name for the CIM server and optionally the port (HostName:port). The default is localhost:5988. The port component is optional. The default is 5988.
- n** *path* Specifies the namespace for the operation. The default is root/cimv2.
- o** *outputformats* Specifies the output format. Valid values are: xml, mof, and table. Default is mof.
- p** *password* Allows the input of a password for the command's server authentication. The default is empty.
- r** *repeat* Sets the number of times to repeat the function. Zero means one time. Repeats the operation without disconnecting. Default is 0.
- sort** Sorts the output objects before they are displayed.
- sum** Presents only summary information, not the complete output. Generally this option presents counts of objects returned instead of the names or objects themselves.
- t** *time* Measures the time for operation and presentation of the results upon command completion.
- timeout** *sec* Sets the connection timeout in seconds. Default is 20.
- trace** *traceLevel* Sets the common components trace. Sets the trace level. 0 is off. Default is 0. Valid values are 0 to 5.
- u** *username* Allows the input of a user name for authentication. The default is empty.

- v Displays verbose data (including operation parameters).
- x Output objects in xml instead of mof format.

The `cimcli` command recognizes the following special options:

- ac *assocClass* Passes the `assocClass` parameter to applicable association operations. Default is to pass no `assocClass` parameter.
- ar *associationRoleName* Defines an association role for associator operations.
- di Specifies the *deepInheritance* parameter for selected commands. The default is 'false'. This option has different meanings for different commands and is used only with the enumerate commands. For further information, refer to the *CIM Operations over HTTP* published by the DMTF.
- i Interactively asks the user to select instances. Used with associator and reference operations.
- ic Sets the CIM operation parameter `classOrigin` in the operation request to true. Only useful with option -o xml.
- iq Sets `includeQualifiers = true`.
- lo Passes `localOnly=true` to applicable operations.
- nlo When set, sets `localOnly = 'false'` on operations. Default is 'false'.


Note that option *localOnly* has been deprecated by the DMTF for some operations and will completely be removed with the next major version of CIM.
- niq Sets `includeQualifiers = 'false'` on operations. Default is 'false'.

Note that option *includeQualifiers* has been deprecated by the DMTF for some operations and will completely be removed with the next major version of CIM.
- pl *propertyNameList* Passes the `propertyNameList` parameter to applicable operations. Format is p1,p2,p3 (without spaces) or "" for an empty list. The default is to pass no `propertyList` parameter.
- r *role* Passes the role parameter to applicable association operations. Default is to pass no role parameter.
- rc *resultClass* Passes the `resultClass` parameter to applicable association operations. Default is to pass no `resultClass` parameter.
- rr *resultRole* Passes the `resultRole` parameter to applicable association operations. Default is to pass no `resultRole` parameter.

cimcli *Instance name*


Instance name

Format 1:



For the getInstance operation, there is also an alternate way to specify an instance name:

Format 2:



Usage

keyPropertyName

to specify an instance, all key properties of the class have to be listed
Specifying a key property with a "=", but without a value assigns the
NULL value to it.

value2 Values separated by a ',' are only valid if you specify an array.

The new syntax listing the key properties separated by spaces now allows to
specify array values.

Examples

Format 1: 'CIM_Person.CreationClassName="",Name="Mike"'

Format 2: CIM_Person CreationClassName= Name=Mike

cimsub

Purpose

The `cimsub` command lets you manage CIM indications on the local CIM server. The command can list, enable, disable and remove indication subscriptions, filters and handlers. However, you cannot modify or create a handler or a filter. The CIM indication must be created or modified by a CIM client program.

list Lists all or selected indication subscriptions, filters, and handlers, and displays the requested information about the instance(s).

enable Enables a specific subscription. Sets a subscription into the enabled state, and the CIM server starts to process it.

disable Disables a specific subscription. Sets a subscription into the disabled state, and it is no longer processed by the CIM server.

remove Removes a specific indication subscription, filter, and/or handler from the CIM server. The information is removed within the CIM server and can only be recreated by a client application. The administrator must take care that a filter or handler is not referenced by any other subscription. If this is the case, but the filter or handler is deleted anyway, this subscription will no longer work.


In order to use the `cimsub` command, the CIM server must be running on the local system and a user needs to have `CONTROL` access to profile `CIMSERV` in class `WBEM`.

Syntax


Main diagram:




list:




enable:



disable:




remove:



Filter:



Handler:



Options

The `cimsub` command recognizes the following options:

- l Lists all or selected
 - indication subscriptions (-ls)
 - filters (-lf)
 - handlers (-lh)

Options -F and -H are superseding the -n namespace option, if -n is set together with either -F or -H.

- e Sets the subscription state to enabled.
- d Sets the subscription state to disabled.
- r Removes a specific
 - indication subscription (-rs)
 - filter (-rf)
 - handler (-rh)
 - or all three together (-ra)

Options -F and -H are superseding the -n namespace option, if -n is set together with either -F or -H.

- v** Displays verbose information (for example, subscription state, filter query, handler destination) for each listed instance.
 - F *[fnamespace:]filtername***
Specifies the name of the filter instance used for the subscription operation. If the filter namespace *[fnamespace:]* is not specified, the operation is using the namespace of the subscription.
 - H *[hnamespace:][hclassname.]handlername***
Specifies the name of the handler instance used for the subscription operation. If the handler namespace *[hnamespace:]* is not specified, the operation is using the namespace of the subscription. If the handler class name *[hclassname.]* is not specified, the operation is using the *CIM_ListenerDestinationCIMXML* handler class name.
- Note:** Currently the only supported handler is an instance of the *CIM_ListenerDestinationCIMXML* class or subclass.
- n *path***
Specifies the namespace for the operation. For the **-l** option, if no namespace is specified, instances in all namespaces are listed. For all other operations, if no namespace is specified, the *cimsub* command operates on instances of the *root/PG_InterOp* namespace.
- Note:** It is recommended not to use any other namespace for indications than *root/PG_InterOp*.
- help** Displays the command help information.
 - version**
Displays the CIM server version.

Examples

The following example lists all subscriptions in the namespace *root/PG_InterOp* in verbose mode:

cimsub -ls -v
Output:

```

Namespace:      root/PG_InterOp
Filter:         root/PG_InterOp:IndicationTest_indicationFilter
Handler:        root/PG_InterOp:CIM_ListenerDestinationCIMXML.IndicationTest
Query:         "SELECT * FROM TestIndication"
Destination:    http://test.server.com/
SubscriptionState: Enabled

```


cimsub -d -F IndicationTest_indicationFilter -H IndicationTest
Disables the subscription specified by **-F** and **-H**, and displays the result in verbose mode.

MODIFY console command

In addition to the `cimconfig` command-line utility (see “`cimconfig`” on page 79), starting with z/OS 1.10 the CIM server configuration can be changed from the z/OS system console using the `MODIFY` command. The general syntax for using the `MODIFY` command to pass information to a UNIX System Services Application is described in *z/OS MVS System Commands*.

Syntax

Following is the specific syntax for using the `MODIFY` command to pass configuration changes to the CIM server. Between the options, no spaces are allowed:



Options

Basically the CIM server accepts the same options for the `MODIFY` command as for the `cimconfig` utility.

jobname

The name of the job that runs the CIM server. When the CIM server is run as a started task, this will usually be `CFZCIM`.

APPL=CONFIG

This is the indicator for the CIM server that a configuration change was requested through the z/OS system console.

property

The name of the configuration property to be changed. For a complete list of CIM server configuration properties see Chapter 9, “CIM server configuration,” on page 53. Typically, the only current configuration properties that you can change dynamically are the *shutdownTimeout* property and the logging and tracing properties. Permanent changes require a CIM server restart. They are indicated using the `PLANNED` keyword at the end of the `MODIFY` command string.

value

The new value for the configuration property to be changed. For values that contain a comma or for case sensitive property values such as path names the value needs to be enclosed in single quotes (`'`). To reset a property to its default value, omit the *value* parameter.

PLANNED

Indicates that the configuration change should be made permanently. This means that the change will only become effective after a CIM server restart, and that the change will also persist further restarts until it is changed again. If `PLANNED` was not specified at the end of the command, the changes will only stay in effect until the next restart of the CIM server.

Examples

F CFZCIM,APPL=CONFIG,traceComponents=xml io

F CFZCIM,APPL=CONFIG,traceLevel=4

Turns on tracing of the CIM server's XML traffic.

F CFZCIM,APPL=CONFIG,enableRemotePrivilegedUserAccess=true,PLANNED

Permanently enables superusers (UID=0) to issue requests against the CIM server from a remote system.

Part 4. Provider reference

Chapter 13. Profiles

A profile defines the CIM model and its behavior that represents a particular domain to be managed. The CIM model comprises CIM classes, associations, indications, properties, methods, and values to describe the domain and its characteristics.

SMI-S profiles

The Storage Management Initiative Specification (SMI-S) was developed by members of the Storage Networking Industry Association (SNIA) and defines an interface for the secure, extensible, and interoperable management of a distributed and heterogeneous storage system. The specification describes the information available to a WBEM client from an SMI-S compliant CIM WBEM server.

The SMI-S specifies standards-based profiles to manage storage networks. It builds on other standards such as CIM. The scope of SMI-S includes storage, storage virtualizers, fibre channel fabrics and IP connectivity, and host storage-specific CIM-based profiles.

The host storage portion of the specification defines profiles for the management of host-based storage devices.

CIM for z/OS supports the host-based storage profiles:

Host Discovered Resources profile

The Host Discovered Resources (HDR) profile defines the model for the storage devices presented to z/OS.

SB Multipath Management profile

The Host Discovered Resource profile defines the model of the logical relationship of a host driver path to a logical unit. The SB Multipath Management profile defines the asynchronous notification of changes applying to this relation, using CIM life cycle indications.

Storage HBA profile

The Storage Host-Bus-Adapter (HBA) profile represents the manageable elements of an HBA and optionally, the storage connected to it, including the HBA Hot Swap Events for HBA creation and deletion, using CIM life cycle indications.

For more information, refer to the SNIA, Storage Management Initiative Specification (SMI-S) website, *Storage Management Technical Specification, Part 6 Host Elements*.

Host Discovered Resources profile

The Host Discovered Resources profile allows a client application to discover

- the storage hardware resources (such as host adapters and storage devices, and including the connectivity and correlatable names) attached to a host system,
- the logical storage resources (such as special files that represent storage devices) available through the operating system, and
- the relationship between these hardware and logical resources.

Figure 5 shows a Host Discovered Resources instance diagram with the host portion consisting of a ComputerSystem and an Initiator SBProtocolEndpoint and the storage controller portion consisting of a Target SBProtocolEndpoint and a LogicalDisk.




Figure 5. Host Discovered Resources Instance Diagram

Used CIM elements

Element name	implementing z/OS class	Reference
CIM_ComputerSystem	IBMzOS_ComputerSystem	see page 129
CIM_LogicalDisk	IBMzOS_LogicalDisk	see page 148
CIM_StorageExtent	IBMzOS_LogicalDisk	see page 148
CIM_SystemDevice	IBMzOS_CSFCPortController	see page 251
CIM_ProtocolEndpoint	IBMzOS_SBProtocolEndpoint	see page 244
Association CIM_HostedAccessPoint	Association IBMzOS_SBHostedAccessPoint	see page 257
Association CIM_Initiator TargetLogicalUnitPath	Association IBMzOS_SBInitiator TargetLogicalUnitPath	see page 258

SB Multipath Management profile

The SB Multipath Management is a subprofile of the Host Discovered Resource profile. This profile provides the asynchronous notification of the creation, state change and deletion of paths between devices and control units. The asynchronous notification is implemented as CIM life cycle indication (CIM_InstCreation, CIM_InstModification, CIM_InstDeletion) for a CIM_InitiatorTargetLogicalUnitPath.

Storage HBA profile

The storage Host-Bus-Adapter (HBA) profile represents the manageable elements of an HBA and optionally, the storage connected to it. An HBA can be connected to disks contained within a server's internal drive cage or an external drive enclosure or array.

Figure 6 shows an HBA instance diagram with the FC Initiator Port Subprofile consisting of an SBProtocolEndpoint and FCPortStatistics, providing data and implementation for FCPort.




Figure 6. HBA instance diagram

HBA Hot Swap Events

The CIM server on z/OS implements the HBA Hot Swap Events for the Storage HBA profile using CIM life cycle indications. The notifications indicate the dynamic insertion (CIM_InstCreation) and deletion (CIM_InstDeletion) of an HBA represented by a CIM_PortController (representing a FICON channel port).

Used CIM elements

Element name	implementing z/OS class	Reference
CIM_FCPort	IBMzOS_FCPort	see page 236
CIM_FCPortStatistics	IBMzOS_FCPortStatistics	see page 239
CIM_PortController	IBMzOS_PortController	see page 241
CIM_Product	IBMzOS_Product	see page 243
CIM_SoftwareIdentity	IBMzOS_SoftwareIdentity	see page 246
CIM_SystemDevice	IBMzOS_CSFCPortController	see page 251
CIM_ProtocolEndpoint	IBMzOS_SBProtocolEndpoint	see page 244
Association CIM_ControlledBy	Association IBMzOS_ControlledBy	see page 249
Association CIM_DeviceSAP Implementation	Association IBMzOS_SBDeviceSAP Implementation	see page 256
Association CIM_ElementSoftwareIdentity	Association IBMzOS _ElementSoftwareIdentity	see page 252
Association CIM_ElementStatisticalData	Association IBMzOS_FCPortStatisticalData	see page 253
Association CIM_HostedAccessPoint	Association IBMzOS_SBHostedAccessPoint	see page 257
Association CIM_InstalledSoftwareIdentity	Association IBMzOS _InstalledSoftwareIdentity	see page 254
Association CIM_Product ElementComponent	Association IBMzOS_Product ElementComponent	see page 255
Association CIM_Initiator TargetLogicalUnitPath	Association IBMzOS_SBInitiator TargetLogicalUnitPath	see page 258

Chapter 14. z/OS Management Instrumentation for CIM

The CIM standard provides the ability to develop management applications that work with systems management data. To work with CIM, developers should have a thorough understanding of the CIM standard defined by the DMTF. For more information about the CIM standard, see Common Information Model (CIM) Standards on the DMTF website.

IBM has developed providers for z/OS that support basic operating system information and some performance metrics. A CIM provider is the link between the CIM server and the system (see Figure 2 on page 5). This interface allows CIM to access and manage the resources. Each CIM provider makes accessible the resources it represents in a standard way.

Notes:

1. **IBM only supports the classes and properties listed in the present document or in other z/OS documentation provided by IBM. All other classes or properties which are not documented by IBM, IBM does not support, and bears no responsibility for their use.**
2. Not all properties of the supported CIM classes described in this document are implemented by z/OS. Those properties implemented by z/OS are documented in each of the following subchapters. For all CIM properties not implemented by z/OS, the CIM server returns no values.

The following CIM classes and associations are implemented as IBM-supplied providers to provide basic operating system information:

Base classes

(See page 126)

- IBMzOS_ComputerSystem: subclass of CIM_ComputerSystem
- IBMzOS_OperatingSystem: subclass of CIM_OperatingSystem
- IBMzOS_OSProcess: subclass of association CIM_OSProcess
- IBMzOS_Process: subclass of CIM_Process
- IBMzOS_RunningOS: subclass of association CIM_RunningOS
- IBMzOS_UnixProcess: subclass of CIM_UnixProcess
- IBMzOS_LogicalDisk: subclass of CIM_LogicalDisk
- IBMzOS_LogicalDiskDevice: subclass of association CIM_SystemDevice

BaseBoard classes

(See page 138)

- IBM_BaseBoard: subclass of CIM_Card
- IBMzOS_BaseBoard: subclass of IBM_BaseBoard

Processor classes

(See page 142)

- IBMzOS_CSProcessor: subclass of association CIM_SystemDevice
- IBMzOS_Processor: subclass of CIM_Processor

File System classes

(See page 150)

- IBMzOS_HostedFileSystem: subclass of association CIM_HostedFileSystem

- IBMzOS_NFS: subclass of CIM_NFS
- IBMzOS_UnixLocalFileSystem: subclass of CIM_UnixLocalFileSystem

Network classes

(See page 154)

- IBMzOS_EthernetPort: subclass of CIM_EthernetPort
- IBMzOS_CSNetworkPort: subclass of association CIM_SystemDevice
- IBMzOS_IPProtocolEndpoint: subclass of CIM_IPProtocolEndpoint
- IBMzOS_NetworkPortImplementsIPEndpoint: subclass of association CIM_PortImplementsEndpoint

Job classes

(See page 160)

- IBMzOS_Job: subclass of CIM_Job
- IBMzOS_JES2Job: subclass of IBMzOS_Job
- IBMzOS_JES3Job: subclass of IBMzOS_Job
- IBMzOS_SysoutDataset: subclass of CIM_LogicalFile
- IBMzOS_JES2SysoutDataset: subclass of IBMzOS_SysoutDataset
- IBMzOS_JES3SysoutDataset: subclass of IBMzOS_SysoutDataset
- IBMzOS_Subsystem: subclass of CIM_Service
- IBMzOS_JobsManagementSettings: subclass of CIM_SettingData
- association IBMzOS_SubsystemJES2Jobs (between IBMzOS_Subsystem and IBMzOS_JES2Job)
- association IBMzOS_SubsystemJES3Jobs (between IBMzOS_Subsystem and IBMzOS_JES3Job)
- association IBMzOS_UsesJES3SysoutDatasets (between IBMzOS_JES3Job and IBMzOS_JES3SysoutDataset)
- association IBMzOS_UsesJES2SysoutDatasets (between IBMzOS_JES2Job and IBMzOS_JES2SysoutDataset)

Cluster classes

(See page 191)

- IBMzOS_Sysplex: subclass of IBMzOS_Cluster
- IBMzOS_SysplexNode: subclass of IBMzOS_ClusterNode
- IBMzOS_CouplingFacility: subclass of IBMzOS_ClusterAggregatedResource
- IBMzOS_CFStructure: subclass of IBMzOS_ClusterAggregatedResource
- IBMzOS_CFStructureConnector: subclass of IBMzOS_ClusterResource
- IBMzOS_ClusterResource
- IBMzOS_ClusterGlobalResource
- IBMzOS_ClusterAggregatedResource
- IBMzOS_Cluster
- IBMzOS_ClusterNode
- IBMzOS_CoupleDataset: subclass of CIM_LogicalFile
- IBMzOS_SysplexCoupleDataset: subclass of IBMzOS_CoupleDataset
- IBMzOS_CFRMCoupleDataset: subclass of IBMzOS_CoupleDataset
- IBMzOS_CouplingFunction: subclass of IBMzOS_ClusterAggregatedResource
- IBMzOS_CFRMPolicy: subclass of IBMzOS_ClusterAggregatedResource

- association IBMzOS_CollectionOfSysplexNodes
- association IBMzOS_CollectionOfCFs
- association IBMzOS_HostedCFStructure
- association IBMzOS_HostedCFStrConnector
- association IBMzOS_CFStructureDependsOn
- association IBMzOS_UsesCFs
- association IBMzOS_UsesCouplingFunctions
- association IBMzOS_UsesSysplexCoupleDatasets
- association IBMzOS_UsesCFRMCoupleDatasets
- association IBMzOS_UsesCFRMPolicies

Cluster indications

- IBMzOS_SysplexInstCreation
- IBMzOS_SysplexInstModification
- IBMzOS_Sysplex_ReallocateInitiated
- IBMzOS_Sysplex_ReallocateCompleted
- IBMzOS_Sysplex_CFRM_CDS_Initialized
- IBMzOS_SysplexNodeInstCreation
- IBMzOS_SysplexNodeInstDeletion
- IBMzOS_SysplexNodeInstModification
- IBMzOS_CouplingFacilityInstCreation
- IBMzOS_CouplingFacilityInstDeletion
- IBMzOS_CouplingFacilityInstModification
- IBMzOS_CFStructureInstCreation
- IBMzOS_CFStructureInstDeletion
- IBMzOS_CFStructureInstModification
- IBMzOS_CFStrConnectorInstCreation
- IBMzOS_CFStrConnectorInstDeletion
- IBMzOS_CFStrConnectorInstModification
- IBMzOS_CollectionOfSysplexNodesInstCreation
- IBMzOS_CollectionOfSysplexNodesInstDeletion
- IBMzOS_CollectionOfCFsInstCreation
- IBMzOS_CollectionOfCFsInstDeletion
- IBMzOS_HostedCFStructureInstCreation
- IBMzOS_HostedCFStructureInstDeletion
- IBMzOS_HostedCFStrConnectorInstCreation
- IBMzOS_HostedCFStrConnectorInstDeletion
- IBMzOS_UsesCFInstCreation: subclass of CIM_InstCreation
- IBMzOS_UsesCFInstDeletion: subclass of CIM_InstDeletion

Storage management classes

(See page 233)

- CIM_StorageExtent
- IBMzOS_FCPort
- IBMzOS_FCPortStatistics
- IBMzOS_PortController
- IBMzOS_Product

- IBMzOS_SBProtocolEndpoint
- IBMzOS_SoftwareIdentity
- association IBMzOS_ControlledBy
- association IBMzOS_CSFCPort
- association IBMzOS_CSFCPortController
- association IBMzOS_ElementSoftwareIdentity
- association IBMzOS_FCPortStatisticalData
- association IBMzOS_InstalledSoftwareIdentity
- association IBMzOS_ProductElementComponent
- association IBMzOS_SBDeviceSAPImplementation
- association IBMzOS_SBHostedAccessPoint
- association IBMzOS_SBInitiatorTargetLogicalUnitPath

Storage management indications

For CIM_PortController:

- CIM_InstCreation
- CIM_InstDeletion

For CIM_InitiatorTargetLogicalUnitPath:

- CIM_InstCreation
- CIM_InstDeletion
- CIM_InstModification

WLM classes

(See page 261)

- IBMzOS_WLM
- association IBMzOS_WLMOS (between IBMzOS_WLM and IBMzOS_ComputerSystem)

WLM indications

- IBMzOS_WLMPolicyActivationIndication

CIM classes implemented by RMF

Please note that for using the CIM providers implemented by RMF you need to have RMF installed and additional configuration is required (see “Setting up the CIM server for RMF monitoring” on page 37). For more information, see *z/OS RMF Programmer’s Guide* and *z/OS RMF User’s Guide*.

- IBMzOS_BaseMetricValue
- IBMzOS_BaseMetricDefinition
- IBMzOS_MetricForME
- IBMzOS_MetricDefForME
- IBMzOS_MetricInstance
- IBMzOS_Channel
- IBMz_CEC
- IBMz_ComputerSystem
- IBMzOS_WLMServiceDefinition
- IBMzOS_WLMServiceClassPeriod

To exploit this functionality, RMF must be installed and running.

Notes:

1. The z/OS Communications Server provides documentation of these CIM classes. For details refer to Considerations for Common Information Model (CIM) providers in *z/OS Communications Server: IP Configuration Guide*.
2. For all classes, the properties that are common for eServer and the z/OS specific properties are documented in separate tables.
3. Starting with z/OS 1.9, the CIM server exploits the functionality of Common event adapter (CEA). CEA is a z/OS component that provides the ability to deliver z/OS events to C-language clients. A CEA address space is started automatically during initialization of every z/OS system. In order for the address space to start successfully, you must configure CEA to work with z/OS. Failure to do so will cause CEA to run in a minimum function mode. For details refer to *z/OS Planning for Installation*.
4. An extra security setup is needed for the Job and Cluster classes.

To understand the syntax of the graphics showing class structures, see “Legend for graphics showing class structures” on page 345.

Supported CIM operations

While the z/OS CIM server supports all of the CIM operations from the DMTF's *CIM Operations over HTTP* specification, only a specific subset of operations is supported by the OS management CIM providers delivered with this release of z/OS.

The following operations are available for all OS management classes or for association classes.

Available for all OS management classes:

- EnumerateInstanceNames
- EnumerateInstances
- GetInstance

Additionally available for all association classes:

- Associators
- AssociatorNames
- References
- ReferenceNames

OS management Base classes




Figure 7. CIM Base classes extended by z/OS-specific classes (1)

Figure 7 on page 126 illustrates the relationship between the IBM extension classes, and the CIM Base classes that they extend. The packages, in which the classes are defined in the CIM Schema, are indicated in parenthesis. The DMTF website provides a detailed description of the CIM base classes. The z/OS-specific classes are described in detail in the following chapters.

The MOF files that define these classes can be found in directory *schemas/os_management* relative to where the providers for z/OS have been installed. The default is */usr/lpp/wbem/provider*.

CIM_ComputerSystem

Purpose

This class represents either virtual or physical computer systems in the sense of a container inside which an operating system may run. This is the central class of the OS Management data model and aggregates all other resource classes.

Inheritance

The z/OS specific subclass is IBMzOS_ComputerSystem (see “IBMzOS_ComputerSystem” on page 129).

Additional subclasses of CIM_ComputerSystem are implemented by RMF, namely IBMz_ComputerSystem (LPARs) and IBMz_CEC. Unless RMF is installed or the RMF CIM providers have been set up appropriately, no instances or errors for those classes will be reported, for example by an *enumerateInstances* operation against class CIM_ComputerSystem. Errors for the classes supported by RMF are only reported when a CIM operation is invoked directly against one of the specific subclasses like IBMz_ComputerSystem.

For further details on classes IBMz_ComputerSystem and IBMz_CEC, see the z/OS *RMF Programmer's Guide*.

CIM_OperatingSystem

Purpose

This class represents a running operating system with its basic properties.

Inheritance

The z/OS specific subclass is IBMzOS_OperatingSystem (see “IBMzOS_OperatingSystem” on page 131).

CIM_OSProcess

Purpose

This class associates an operating system with the set of currently active address spaces and UNIX System Services processes.

Inheritance

The z/OS specific subclass is IBMzOS_OSProcess (see “IBMzOS_OSProcess” on page 133).

CIM_Process

Purpose

This class represents currently active processes on an operating system. For z/OS this is mapped to address spaces and UNIX System Services processes.

Inheritance

The z/OS specific subclasses are:

- IBMzOS_Process (for address spaces) (see “IBMzOS_Process” on page 134)
- IBMzOS_UnixProcess (for UNIX System Services processes) (see “IBMzOS_UnixProcess” on page 137)

CIM_RunningOS

Purpose

This class associates a computer system with the currently running operating system (see Figure 7 on page 126).

Inheritance

The z/OS specific subclass is IBMzOS_RunningOS (see “IBMzOS_RunningOS” on page 136).

IBMzOS_ComputerSystem

Purpose

This class provides basic computer system information such as computer name, and status information. A provider instruments this class so that it can be used by client applications to identify the managed system on which the provider is running (typically a server or an application).

Inheritance

CIM_ManagedElement
↳ CIM_ManagedSystemElement
↳ CIM_LogicalElement
↳ CIM_EnabledLogicalElement
↳ CIM_System
↳ CIM_ComputerSystem
↳ IBMzOS_ComputerSystem

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_ComputerSystemProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiOSBase_ComputerSystemProvider.so

Used by the following CIM profiles

- Host Discovered Resources Profile
- IBM OS management

Properties

The following properties are common for eServer:

string Caption	Always set to IBM z/OS Computer System.
string Description	Always set to This is an IBMzOS_ComputerSystem.
string ElementName	Returns IBM: <i>model</i>
string Name [key]	The fully qualified IP host name.
string CreationClassName [key]	Always set to IBMzOS_ComputerSystem
string NameFormat	Describes the format used to build the Name property. Always set to IP.
uint16 Dedicated[]	Indicates whether this is a special purpose system. Always set to 0 (not dedicated).
string UUID	The universally unique identifier of the server. For z/OS, no value is supplied for this property, but it is maintained for compatibility with the other IBM eServer platforms.
string HostingSystemName	A name that identifies the underlying hosting

system in a virtualized environment. Returns *Elementname + serialnumber*.

string HostingSystemNameFormat

The name format used for HostingSystemName. Always returns 0ther.

The following properties have data that may be specific to z/OS, or may map to z/OS specific attributes.

string LPARName	Name of the zSeries® logical partition that makes up the computer system. If not running in LPAR mode, a blank string is returned here.
string VMGuestID	z/VM® user ID of the virtual machine, of which the current z/OS image is a guest. If z/OS is not running as a guest under z/VM, a blank string is returned here.
string CPUID	String containing the readable part of the serial number concatenated with the model number.
string SerialNumber	IBM allocated number used to identify the server on which this computer system is running.
string MachineType	Processor family of this z/OS server.
string Model	Model number of the server.
string Manufacturer	The name of the company that produced the server.
uint16 LPARid	Logical partition number. This number distinguishes the configuration from all other level-2 configurations provided by the same LPAR hypervisor.
string Plant	Plant of manufacturer for the CPU.

IBMzOS_OperatingSystem

Purpose

This class is for use by client applications to obtain basic properties of a running z/OS operating system.

Inheritance

CIM_OperatingSystem
← IBMzOS_OperatingSystem

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_OperatingSystemProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiOSBase_OperatingSystemProvider.so

Properties

The following properties are common for eServer:

string Name [key]	The name of the z/OS operating system.
uint16 OperationalStatus[]	Overall system status.
uint16 OSType	Always 68 ('z/OS').
string Version	Version, release and modification of the operating system in the format of "VV.RR.MM". For example, for z/OS V1.7.0, this will return "01.07.00".
datetime LastBootUpTime	Time when the operating system was IPLed.
datetime LocalDateTime	Local time of the operating system
sint16 CurrentTimeZone	Time zone for the operating system, offset in minutes from GMT.
uint32 NumberOfUsers	The number of currently logged on TSO and UNIX System Services users.
uint32 NumberOfProcesses	Total number of UNIX processes and active address spaces.
uint32 MaxNumberOfProcesses	The maximum number of processes configured in MaxProcSys.
uint64 MaxProcessMemorySize	The maximum number of KBytes of memory that can be allocated to a process (RLIMIT_AS).
uint64 TotalVirtualMemorySize	Total number of KBytes of virtual memory available to the operating system.
uint64 FreeVirtualMemory	Number of KBytes of virtual memory currently unused and available.

uint64 FreePhysicalMemory Number of KBytes of physical memory currently unused and available.

uint64 TotalVisibleMemorySize The total amount of physical memory (in KBytes) available to the operating system.

uint64 SizeStoredInPagingFiles The total number of KBytes that can be stored in the operating system's page data sets.

uint64 FreeSpaceInPagingFiles The total number of KBytes currently free in the operating system's page data sets.

The following properties have data that may be specific to z/OS, or may map to z/OS specific attributes.

string LanguageEdition eServer specific extension for the language version of the OS. For z/OS always returns '*en-US*'.

string CodeSet eServer specific extension for the default OS code page. For z/OS this returns the code page for the CIM server process.

uint32 DefaultPageSize eServer specific extension. The default size of pages used by the virtual memory management in units of bytes. Always 4096 for z/OS.

string SysplexName The name of the z/OS Sysplex to which this operating system belongs.

string FMID Function modification identifier of the z/OS operating system.

uint32 LastBootUpDuration Indicates the time in seconds used to complete the IPL.

string IPLProfile[] HMC profile from which the operating system was IPLed. IPLProfile contains 4 elements:

ipaiofdu	IODF unit address
ipalloads	LOADxx suffix
ipaprompt	Operator prompt flag
ipanucid	Nucleus ID

string sequentialReleaseNumber Release number of the operating system as an ever increasing number, e.g. 21.00 for z/OS 1.11.

IBMzOS_OSProcess

Purpose

This class provides a link between the operating system and process(es) running in the context of this operating system. Client applications can use this provider to give clients an understanding of the processes (jobs) running on the managed system within the context of its operating system.

Inheritance

CIM_OSProcess
← IBMzOS_OSProcess

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_OSProcessProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_OSProcessProvider.so

IBMzOS_Process

Purpose

This class provides basic process information such as process name, priority, and run-time state. Instances of class IBMzOS_Process are mapped to z/OS address spaces. Client applications can use this class to give clients an understanding of the processes (address spaces) running on the managed system within the context of their operating system.

Note: z/OS also provides the notion of a UNIX process through the UNIX System Services. In addition, those processes running under UNIX System Services are supported by the extra IBMzOS_UnixProcess class which is derived from class CIM_UnixProcess. When a client enumerates all instances of class CIM_Process, it gets the complete list of z/OS address spaces, as well as all processes running under UNIX System Services. However, if the client enumerates the instances of class IBMzOS_Process directly, it only gets the list of address spaces since class IBMzOS_UnixProcess is not derived from IBMzOS_Process but only from CIM_UnixProcess. Ideally, IBMzOS_UnixProcess should inherit from IBMzOS_Process, besides inheriting from CIM_UnixProcess, however, multiple inheritance is not the current standard in CIM version 2. For inheritance information of the mentioned classes refer to Figure 7 on page 126.

Inheritance

CIM_Process
← IBMzOS_Process

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_ProcessProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiOSBase_ProcessProvider.so

Properties

The following properties are common for eServer:

string Name	The name of the z/OS address space.
string Handle [key]	The decimal representation of the address space ID(ASID).
uint32 Priority	The address space's dispatching priority.
datetime CreationDate	The time when the address space was created.
uint64 KernelModeTime	Not supported for z/OS.
uint64 UserModeTime	Not supported for z/OS.

The following properties have data that may be specific to z/OS, or may map to z/OS specific attributes:

string ProcessOwner	The primary z/OS user ID under which an address space was started.
----------------------------	--

uint16 ProcessType

The type of address space. Possible values are: 0 (Other), 1 (TSO User), 2 (Started Task), 3 (Job), 4 (System Address Space), 5 (Initiator).

IBMzOS_RunningOS

Purpose

This class is for use by clients to find associations between a computer system and the operating system that is currently running on the computer system.

Inheritance

CIM_OperatingSystem

← IBMzOS_OperatingSystem

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_RunningOSProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_RunningOSProvider.so

IBMzOS_UnixProcess

Purpose

This class provides basic information about z/OS processes running in the UNIX System Services subsystem. It supports all properties from CIM_Process plus a set of properties typical for UNIX processes.

Inheritance

Class IBMzOS_UnixProcess is not derived from IBMzOS_Process, and therefore no instances of IBMzOS_UnixProcess are returned when a client enumerates the instances of class IBMzOS_Process, rather than class CIM_Process.

CIM_Process

← IBMzOS_UnixProcess

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_UnixProcessProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiOSBase_UnixProcessProvider.so

Properties

The following properties are common for eServer:

string Name	The name of the z/OS UNIX process. This is usually the name of the executable that started the process.
string Handle [key]	The z/OS UNIX process ID.
uint32 Priority	The process priority.
uint16 ExecutionState	The process state (ready, blocked, suspended, stopped, and so on).
datetime CreationDate	The time when the process was started.
uint64 KernelModeTime	Not supported on z/OS.
uint64 UserModeTime	Not supported on z/OS.
string ParentProcessID	The parent process ID.
uint64 RealUserID	The real user ID.
uint64 ProcessGroupID	The process group ID.
uint64 ProcessSessionID	The process session ID.
string ProcessTTY	The TTY currently associated with this process.
string ModulePath	The executing process's command path.
string Parameters[]	The operating system parameters provided to the executing process. These are the argv[] values.

Class IBMzOS_UnixProcess has no z/OS specific properties.

OS management BaseBoard classes

Figure 8 illustrates the relationship between the IBM extension classes, and the CIM BaseBoard classes that they extend. The packages, in which the classes are defined in the CIM Schema, are indicated in parenthesis. The DMTF website provides a detailed description of the CIM BaseBoard classes. The z/OS-specific classes are described in detail in the following chapters.




Figure 8. OS management BaseBoard Class

IBM_BaseBoard

Purpose

This class represents the unique characteristics of the physical hardware as recognized by the z/OS operating system running on that hardware (the inband view). On most platforms these are the characteristics of the main board, and therefore, the name IBM_BaseBoard was chosen for this class. Instances of this class are either identified by a unique ID that was assigned to the main board (property *UUID*) or by the combination of manufacturer, model and serial number. The major purpose of this class is to provide the ability to determine which instances of computer systems are running on the same physical hardware.

Inheritance

The z/OS specific subclass is IBMzOS_BaseBoard (see “IBMzOS_BaseBoard” on page 140).

Properties

The following properties are common for eServer:

string Caption	Always returns <i>'Base Board'</i> .
string Description	Always returns <i>'A class derived from Card to deliver the systems base board hardware information.'</i>
string ElementName	Same as property <i>Tag</i> .
string Tag [key]	A combination of manufacturer, model and serial number in the following format: manufacturer:model:serialnumber.
string CreationClassName [key]	Always returns <i>'IBMzOS_BaseBoard'</i> .
string SerialNumber	IBM allocated number used to identify the CEC.
string Model	The model number of the CEC, for example <i>'314'</i> .
string Manufacturer	The name of the company that produced the CEC.
string PartNumber	Not supported for z/OS.
boolean HostingBoard	Always returns TRUE, indicating that this card is a main board.
string UUID	The unique ID assigned to the main board. For z/OS, no value is supplied for this property, but it is maintained for compatibility with the other IBM eServer platforms.

IBMzOS_BaseBoard

Inheritance

IBM_BaseBoard
← IBMzOS_BaseBoard

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_BaseBoardProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiOSBase_BaseBoardProvider.so

Properties

The following properties have data that may be specific to z/OS, or may map to z/OS specific attributes.

string MachineType	Processor type for the class of this z/OS server, for example: 2084
uint16 Family	The processor family. For z/OS, a value of 204 (z/Architecture® base) is returned.
uint32 NumberOfProcessors	The number of general purpose processors installed on the system board.
uint32 MemorySize	The total amount of physical memory (in Kbytes) available to the operating system through which this data was provided. Note that this is not the total amount of installed memory for the zSeries CEC. This is the inband view of z/OS.
uint16 Architecture	The processor architecture.
uint32 NumberAndTypeOfProcessors[]	An array of uint32 where the first element is the number of general purpose processors, the second element is the number of zAAPs, the third element is the number of zIIPs, if supported.
uint16 LPARId	Logical partition number. This number distinguishes the configuration from all other level-2 configurations provided by the same LPAR hypervisor.
string Plant	Plant of manufacturer for the CPU.

Association CIM_ComputerSystemPackage

Purpose

This class associates a ComputerSystem with the physical main board of the system on which it runs.

Inheritance

The z/OS specific subclass is IBMzOS_CSBaseBoard (see “Association IBMzOS_CSBaseBoard”).

Association IBMzOS_CSBaseBoard

Purpose

This class associates a z/OS computer system with the physical zSeries CEC on which it runs (see Figure 8 on page 138). It has no properties.

Inheritance

CIM_ComputerSystemPackage
← IBMzOS_CSBaseBoard

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CSBaseBoardProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CSBaseBoardProvider.so

OS management Processor classes

Figure 9 illustrates the relationship between the IBM extension classes, and the CIM Processor classes that they extend. The packages, in which the classes are defined in the CIM Schema, are indicated in parenthesis. The DMTF website provides a detailed description of the CIM Processor classes. The z/OS-specific classes are described in detail in the following chapters.




Figure 9. OS management Processor classes

CIM_Processor

Purpose

This class represents the physical processors that are available to the operating system.

Inheritance

The z/OS specific subclass is IBMzOS_Processor (see “IBMzOS_Processor” on page 144).

Association CIM_SystemDevice

Purpose

This class associates a ComputerSystem with the instrumented processors.

Inheritance

The z/OS specific subclass is IBMzOS_CSProcessor.

IBMzOS_Processor

Inheritance

CIM_Processor
← IBMzOS_Processor

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_ProcessorProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libIBMzOS_Processor.so

Properties

The following properties are common for eServer:

string Caption	Always set to 'zSeries logical processor'.								
string Description	Always set to 'This class represents instances of processors currently available to the z/OS operating system'.								
string ElementName	Same as DeviceID.								
string DeviceID [key]	Concatenation of the CPUID of the physical processor (PCCACPID) + colon (':') + CPU address. CBA987654321:2 is an example for a valid DeviceID. If a CPU is in Reserved or Offline state, the CPUID is FFFFFFFFFF.								
uint16 EnabledState	<table><tr><td>2</td><td>Online</td></tr><tr><td>3</td><td>Reserved</td></tr><tr><td>6</td><td>Offline</td></tr><tr><td>9</td><td>Offline by WLM</td></tr></table>	2	Online	3	Reserved	6	Offline	9	Offline by WLM
2	Online								
3	Reserved								
6	Offline								
9	Offline by WLM								
string Role	<table><tr><td>CP</td><td>Central Processor (including zEAP Processors)</td></tr><tr><td>ZIIP</td><td>zIIP processor</td></tr><tr><td>ZAAP</td><td>zAAP processor</td></tr><tr><td>UNKNOWN</td><td>no assigned role</td></tr></table>	CP	Central Processor (including zEAP Processors)	ZIIP	zIIP processor	ZAAP	zAAP processor	UNKNOWN	no assigned role
CP	Central Processor (including zEAP Processors)								
ZIIP	zIIP processor								
ZAAP	zAAP processor								
UNKNOWN	no assigned role								
uint16 Family	200 (= 'S/390® and zSeries Family').								
string OtherFamilyDescription	'S/390 and zSeries Family' or specific model like 'z990'.								
uint32 MaxClockSpeed	Not supported for z/OS.								
uint32 CurrentClockSpeed	Not supported for z/OS.								

uint16 LoadPercentage	For z/OS provided through RMF metrics provider only.
string Stepping	Not supported for z/OS.
string UniqueID	CPUID of the physical processor (PCCACPID).
uint16 CPUStatus	Not supported for z/OS.

Class IBMzOS_Processor has no z/OS specific properties.

Methods

Method	Description																			
unit32 RequestStateChange()	Issues messages for the operator or automation to change the state of the processor.																			
	<table> <tr> <th>Parameters</th><th>Description</th></tr> <tr> <td>[IN] uint16 RequestedState</td><td>Must be one of "Enabled" (2) or "Offline" (6).</td></tr> <tr> <td>[OUT] CIM_ConcreteJob REFJob</td><td>Always returns NULL.</td></tr> <tr> <td>[IN] datetime TimeoutPeriod</td><td>Must be either not defined or a CIM NULL value.</td></tr> <tr> <th>Return values</th><th>Description</th></tr> <tr> <td>0</td><td>Completed without Error</td></tr> <tr> <td>4</td><td>Due to a system error the state change cannot take place. Check target system log.</td></tr> <tr> <td>5</td><td>Parameter <i>RequestedState</i> has not the value "Enabled" (2) or "Offline" (6).</td></tr> <tr> <td>4097</td><td>If the state change is different than from "Reserved" (3), "Offline" (6) to "Online" (2) or from "Online" (2) to "Offline" (6).</td></tr> <tr> <td>4098</td><td>If TimeoutPeriod is not 0 or NULL.</td></tr> </table>	Parameters	Description	[IN] uint16 RequestedState	Must be one of "Enabled" (2) or "Offline" (6).	[OUT] CIM_ConcreteJob REFJob	Always returns NULL.	[IN] datetime TimeoutPeriod	Must be either not defined or a CIM NULL value.	Return values	Description	0	Completed without Error	4	Due to a system error the state change cannot take place. Check target system log.	5	Parameter <i>RequestedState</i> has not the value "Enabled" (2) or "Offline" (6).	4097	If the state change is different than from "Reserved" (3), "Offline" (6) to "Online" (2) or from "Online" (2) to "Offline" (6).	4098
Parameters	Description																			
[IN] uint16 RequestedState	Must be one of "Enabled" (2) or "Offline" (6).																			
[OUT] CIM_ConcreteJob REFJob	Always returns NULL.																			
[IN] datetime TimeoutPeriod	Must be either not defined or a CIM NULL value.																			
Return values	Description																			
0	Completed without Error																			
4	Due to a system error the state change cannot take place. Check target system log.																			
5	Parameter <i>RequestedState</i> has not the value "Enabled" (2) or "Offline" (6).																			
4097	If the state change is different than from "Reserved" (3), "Offline" (6) to "Online" (2) or from "Online" (2) to "Offline" (6).																			
4098	If TimeoutPeriod is not 0 or NULL.																			

OS management Logical Disk classes

Figure 10 on page 147 illustrates the relationship between the IBM extension classes, and the CIM Base classes that they extend. This figure focuses on class IBMzOS_LogicalDisk which was provided in z/OS 1.9 CIM server to support the management of logical disks.

The packages, in which the classes are defined in the CIM Schema, are indicated in parenthesis.

The DMTF website provides a detailed description of the CIM Base classes. The z/OS-specific classes are described in detail in the following chapters.

Note: The described metrics are only available for active disks, but not for inactive or offline disks.



Purpose

Inheritance

Chapter 14. z/OS Management Instrumentation for CIM 147

IBMzOS_LogicalDisk

Purpose

This class provides basic information about disk devices known to the z/OS operating system based on the logical view.

Inheritance

CIM_ManagedElement
↳ CIM_ManagedSystemElement
↳ CIM_LogicalElement
↳ CIM_EnabledLogicalElement
↳ CIM_LogicalDevice
↳ CIM_StorageExtent
↳ CIM_LogicalDisk
↳ IBMzOS_LogicalDisk

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_LogicalDiskProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_LogicalDiskProvider.so

Used by the following CIM profiles

- Host Discovered Resources profile

Properties

string Caption	Always returns z/OS Storage Volume.
string Description	Always returns Represents a storage volume as seen by z/OS.
string ElementName	Same as Name (Volume Serial Number)
string Name	Unique identifier for the extent in the form <i>CC:SS:DDDD</i> , where <i>CC</i> is the channel subsystem ID <i>SS</i> is the SubchannelSetID <i>DDDD</i> is the DeviceNumber
uint16 NameFormat	Returns 12 OS device name format
uint16 NameNamespace	Returns 8 OS device namespace
uint16 EnabledState	Mapped from the UCBONLI and UCBBBOX values retrieved through UCBSKAN. See Table 7 on page 149 for mapping values of <i>EnabledState</i> to system data.
string CreationClassName	Always returns IBMzOS_LogicalDisk.

string DeviceID	Channel Device ID obtained from UCBCHAN through UCBSCAN
string[] IdentifyingDescriptions	[0]=Device Node Element Description obtained from the NEDID field of the matching IHACDR control block.
string[] OtherIdentifyingInfo	[0]="Device Node Element Descriptor"
string SystemCreationClassName	Always returns IBMzOS_ComputerSystem.
string SystemName	The systems fully qualified hostname (see <i>IBMzOS_ComputerSystem:colon;Name</i>). Obtained through the <i>OSBase_Common.get_system_name()</i> function.
uint16 OperationalStatus[]	Returns <ul style="list-style-type: none"> 0 Unknown 2 OK 9 Stopping 10 Stopped

The property *enabledState* is set based on the UCB control block information as shown in the following table:

Table 7. UCB control block information

UCBONLI	UCBBOX	
	Boxed	Not boxed
Online	Quiesce (9)	Enabled (2)
Offline	Disabled (3)	Disabled (3)
Pending Offline	Shutting down (4)	

Associations

IBMzOS_SBInitiatorTargetLogicalUnitPath

Source	IBMzOS_LogicalDisk
Target	CIM_ProtocolEndpoint
see	page 258

IBMzOS_LogicalDiskDevice

Source	IBMzOS_ComputerSystem
Target	IBMzOS_LogicalDisk

OS management File System classes

Figure 11 illustrates the relationship between the IBM extension classes, and the CIM FileSystem classes that they extend. The packages, in which the classes are defined in the CIM Schema, are indicated in parenthesis. The DMTF website provides a detailed description of the CIM FileSystem classes. The z/OS-specific classes are described in detail in the following chapters.




Figure 11. OS management File System classes

CIM_LocalFileSystem

Purpose

This class represents file systems that are locally attached to a computer system. On z/OS, hierarchical file systems HFS and zFS are supported.

Inheritance

The z/OS specific subclass is IBMzOS_UnixLocalFileSystem (see “IBMzOS_UnixLocalFileSystem” on page 152).

CIM_RemoteFileSystem

Purpose

This class represents file systems that are accessed remotely by a computer system. On z/OS, only NFS is supported.

Inheritance

The z/OS specific subclass is IBMzOS_NFS (see “IBMzOS_NFS” on page 153).

Association CIM_HostedFileSystem

Purpose

The CIM_HostedFileSystem association associates a ComputerSystem with the set of currently mounted UNIX System Services file systems.

Inheritance

The z/OS specific subclass is IBMzOS_HostedFileSystem.

IBMzOS_UnixLocalFileSystem

Inheritance

CIM_LocalFileSystem

← IBMzOS_UnixLocalFileSystem

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_UnixLocalFileSystemProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libIBMzOS_UnixLocalFileSystem.so

Properties

The following properties are common for eServer:

string Caption	Always set to <i>'z/OS hierarchical local file system'</i> .
string Description	Always set to <i>'This class represents instances of currently mounted local hierarchical file systems'</i> .
string ElementName	Same as Name.
string Name [key]	File system name (z/OS data set name).
string Root	Name of the directory where the file system is mounted.
uint64 FileSystemSize.	File system size in bytes.
uint64 AvailableSpace	Space available on the file system in bytes.
boolean ReadOnly	Indicates whether the file system is mounted read only.
string FileSystemType	File system type, for example <i>'NFS'</i> .

The following properties have data that may be specific to z/OS, or may map to z/OS specific attributes.

DDName	DD name that was specified on mount.
FSParentDeviceID	Device ID of the parent file system.
FSDeviceID	Device number which the STAT command will return for all files in this file system.
MountParameters	The parameters that were specified for the mount command.
FSOwner	MVS Owner ID of the file system.
FSTypeName	The file system type name from the PARMLIB statement.

IBMzOS_NFS

Inheritance

CIM_RemoteFileSystem
← IBMzOS_NFS

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_NFSProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libIBMzOS_NFS.so

Properties

The following properties are common for eServer:

string Caption	Always set to ' <i>z/OS mounted network file system</i> '.
string Description	Always set to ' <i>This class represents instances of currently mounted network file systems</i> '.
string ElementName	Same as Name.
string Name [key]	File system name (corresponds to the <i>file system</i> argument of the <i>mount</i> command).
string Root	Name of the directory where the file system is mounted.
uint64 FileSystemSize	File system size in bytes.
uint64 AvailableSpace	Space available the on file system in bytes.
boolean ReadOnly	Indicates whether the file system is mounted read only.
string FileSystemType	File system type, for example ' <i>NFS</i> '.

Class IBMzOS_NFS has no z/OS specific properties.

OS management Network classes

The classes described in this section are implemented by the z/OS Communication Server. For details on these CIM classes, refer to *z/OS Communications Server: IP Configuration Guide*.

The providers are installed in the `/usr/lpp/tcpip/lib` hierarchical file system directory and linked to the CIM server's provider directory.

The z/OS CS CIM class definition and provider registration files are installed in the `/usr/lpp/tcpip/mof` hierarchical file system directory and are already integrated into the CIM server.

Figure 12 on page 155 illustrates the relationship between the IBM extension classes, and the CIM Network classes that they extend. The packages, in which the classes are defined in the CIM Schema, are indicated in parenthesis. The DMTF website provides a detailed description of the CIM BaseBoard classes. The z/OS-specific classes are described in detail in the following chapters.




Figure 12. OS management Network classes

CIM_EthernetPort

Purpose

This class represents network ports (interfaces) of type Ethernet. For z/OS, all the Ethernet interfaces configured to the TCP/IP stacks on the MVS image are supported.

Inheritance

The z/OS specific subclass is IBMzOS_EthernetPort (see “IBMzOS_EthernetPort” on page 157).

CIM_IPProtocolEndpoint

Purpose

This class represents the installed IP protocols. For z/OS, all IPv4 addresses configured to the TCP/IP stacks on the MVS image are supported.

Inheritance

The z/OS specific subclass is IBMzOS_IPProtocolEndPoint (see “IBMzOS_IPProtocolEndpoint” on page 158).

CIM_PortImplementsEndpoint

Purpose

This class associates a network port with its installed network protocols. Currently, only IP protocols defined for Ethernet ports are returned.

Inheritance

The z/OS specific subclass is IBMzOS_NetworkPortImplementsIPEndpoint.

Association CIM_SystemDevice

Purpose

This class associates a ComputerSystem with the instrumented network ethernet ports.

Inheritance

The z/OS specific subclass is IBMzOS_CSNetworkPort.

IBMzOS_EthernetPort

Inheritance

CIM_EthernetPort
← IBMzOS_EthernetPort

Provider module

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_EthernetPortProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiOSBase_EthernetPortProvider.so

Owning component

The z/OS component which owns the CMPI provider is

Communication Server

Properties

The following properties are common for eServer:

string Caption	Always set to 'IBMzOS EthernetPort'.
string Description	Variable, depending on the type of interface, for example, 'IP Assist Queued Direct I/O Ethernet protocol port'.
string ElementName	Same as Name.
string Name	The label by which the NetworkPort is known to the operating system ('tcpprocname_intfname').
uint16 EnabledState	Indicates whether the protocol endpoint is active or not.
string DeviceID [key]	Identifying information to uniquely name the ethernet port. ('tcpprocname_intfname').
uint64 Speed	The current bandwidth of the port in bits per second.
uint64 MaxSpeed	The maximum bandwidth of the port in bits per second. For z/OS, this is always the same value as <i>Speed</i> .
uint16 LinkTechnology	Always 2 (=Ethernet).
string OtherLinkTechnology	Not set for z/OS.

The following properties have data that may be specific to z/OS, or may map to z/OS specific attributes.

TcpipProcName z/OS TCP/IP stack name.

IBMzOS_IPProtocolEndpoint

Inheritance

CIM_IPProtocolEndpoint

← IBMzOS_IPProtocolEndpoint

Provider module

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_IPProtocolEndpointProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiOSBase_IPProtocolEndpointProvider.so

Owning component

The z/OS component which owns the CMPI provider is

Communication Server

Properties

The following properties are common for eServer:

string Caption

Always set to 'IBMzOS Protocol Endpoint for IP'.

string Description

Always set to 'A communication point to send and receive data. This class is dedicated to relate IP interfaces to Logical Networks'.

string ElementName

Same as Name.

string Name [key]

The unique name of the protocol endpoint, constructed according to the template in NameFormat.

uint16 EnabledState

Returns whether the protocol endpoint is active or not.

string NameFormat

Describes the format of the name property. For z/OS, this is always set to 'TCPIPPROCNAME_TYPE_DEVICE_IPADDR(_ETH)'.

string IPv4Address

The IPv4 IP address.

string IPv6Address

Not yet supported for z/OS instrumentation.

string SubnetMask

The IPv4 IP subnet mask.

uint16 IPVersionSupport

Always returns 1 (=IPv4 only).

The following properties have data that may be specific to z/OS, or may map to z/OS specific attributes.

TcpipProcName

z/OS TCP/IP stack name.

OS management Job classes

The classes described in this section are implemented by z/OS to instrument the z/OS jobs subsystems, JES2 and JES3.

For using these providers you need an extra security setup as described in “Setting up the CIM server for Cluster, CoupleDataset, and JES2-JES3Jobs providers” on page 38.

For a list of the Jobs providers' reason codes, see “Appendix C. CEA reason codes” on page 339.

IBMzOS_JES2Job

Purpose

This class is a subclass of IBMzOS_Job and contains those properties that are unique to a job that has run, or will run, under JES2.

Inheritance

IBMzOS_Job
← IBMzOS_JES2Job

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_JES2JobProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_JES2JobProvider.so

Properties

The following properties have been implemented for z/OS:

string Caption	A short description of the class. Returns <i>'IBM z/OS JES2 Job'</i> .																								
string Description	A description of the class. Returns <i>'This is an IBMzOS_JES2Job'</i> .																								
string ElementName	Name given to this instance of the class (same as Name)																								
datetime InstallDate	Not supported for z/OS.																								
string Name [key]	The property is overridden by <i>IBMzOS_JES2Job</i> . It contains a unique identifier for this job.																								
uint16 OperationalStatus[]	The current status of the JES2 job. <table><tr><td>1</td><td>No subchain exists</td></tr><tr><td>2</td><td>Active in CI in FSS address space</td></tr><tr><td>3</td><td>Awaiting postscan (batch)</td></tr><tr><td>4</td><td>Awaiting postscan (damsel)</td></tr><tr><td>5</td><td>Awaiting volume fetch</td></tr><tr><td>6</td><td>Awaiting start setup (JES3), Awaiting setup (JES2)</td></tr><tr><td>7</td><td>Awaiting/active in MDS system select processing</td></tr><tr><td>8</td><td>Awaiting resource allocation</td></tr><tr><td>9</td><td>Awaiting unavailable volumes</td></tr><tr><td>10</td><td>Awaiting volume mounts</td></tr><tr><td>11</td><td>Awaiting/active in MDS system verify processing</td></tr><tr><td>12</td><td>Error during MDS processing</td></tr></table>	1	No subchain exists	2	Active in CI in FSS address space	3	Awaiting postscan (batch)	4	Awaiting postscan (damsel)	5	Awaiting volume fetch	6	Awaiting start setup (JES3), Awaiting setup (JES2)	7	Awaiting/active in MDS system select processing	8	Awaiting resource allocation	9	Awaiting unavailable volumes	10	Awaiting volume mounts	11	Awaiting/active in MDS system verify processing	12	Error during MDS processing
1	No subchain exists																								
2	Active in CI in FSS address space																								
3	Awaiting postscan (batch)																								
4	Awaiting postscan (damsel)																								
5	Awaiting volume fetch																								
6	Awaiting start setup (JES3), Awaiting setup (JES2)																								
7	Awaiting/active in MDS system select processing																								
8	Awaiting resource allocation																								
9	Awaiting unavailable volumes																								
10	Awaiting volume mounts																								
11	Awaiting/active in MDS system verify processing																								
12	Error during MDS processing																								

13	Awaiting selection on main (JES3), Awaiting execution (JES2)
14	Scheduled on main (JES3), Active executing (JES2)
17	Awaiting breakdown (JES3), Active in output (JES2)
18	Awaiting MDS restart processing
19	Main MDS processing complete
20	Awaiting output service (JES3), Awaiting hardcopy (JES2)
21	Awaiting output service writer
22	Awaiting reserved services
23	Output service complete
24	Awaiting selection on main (demand select job)
25	Ending function rq waiting or I/O completion
26	Ending function rq not processed
27	Maximum rq index value
128	Active in input processing
129	Awaiting conversion
130	Active in conversion
131	Active in setup
132	Active in spin
133	Awaiting output
134	Awaiting purge
135	Active in purge
136	Active on NJE sysout received
137	Awaiting NJE transmission
138	Active on NJE job transmitter
string StatusDescriptions[]	Strings describing the various <i>OperationalStatus</i> values. Returns NULL.
string Status	Not supported for z/OS.
string JobStatus	A free form string containing information about the job. The primary job status is reflected in <i>OperationalStatus</i> . <i>JobStatus</i> provides additional implementation-specific details.
datetime TimeSubmitted	The time that the Job was submitted to execute. A value of all zeros indicates that the owning element is not capable of reporting a date and time. Therefore, the <i>ScheduledStartTime</i> and <i>StartTime</i> are reported as intervals relative to the time their values are required.
datetime ScheduledStartTime	Not supported for z/OS.
datetime StartTime	The time that the Job was actually started. This may be represented by an actual date and time, or by an interval relative to the time that this property is requested.

	<p>Note that this property is also present in the <code>JobProcessingStatistics</code> class. This is necessary to capture the processing information for recurring Jobs, since only the 'last' run time can be stored in this single-valued property.</p>
datetime ElapsedTime	<p>The time interval that the Job has been executing or the total execution time if the Job is complete.</p> <p>Note that this property is also present in the <code>JobProcessingStatistics</code> class. This is necessary to capture the processing information for recurring Jobs, since only the 'last' run time can be stored in this single-valued property.</p>
uint32 JobRunTimes	<p>Number of times that the Job should be run.</p> <p>A value of 1 indicates that the Job is NOT recurring, while any non-zero value indicates a limit to the number of time that the Job will recur.</p> <p>Zero indicates that there is no limit to the number of times that the Job can be processed, but that it is terminated either AFTER the <i>UntilTime</i>, or by manual intervention.</p> <p>By default, a job is processed once.</p> <p>This property is not modifiable.</p>
uint8 RunMonth	Not supported for z/OS.
sint8 RunDay	Not supported for z/OS.
sint8 RunDayOfWeek	Not supported for z/OS.
datetime RunStartInterval	<p>The time interval after midnight when the Job should be processed.</p> <p>For example, 00000000020000.000000:000 indicates that the Job should be run on or after two o'clock, local time of UTC time (distinguished using the <i>LocalOrUtcTime</i> property).</p> <p>This property is not modifiable.</p>
uint16 LocalOrUtcTime	<p>This property indicates whether the time represented in the <i>RunStartInterval</i> and <i>UntilTime</i> properties represent local or UTC times.</p> <p>Time values are synchronized worldwide by using the enumeration value 2, "UTC Time". Permitted values are:</p> <ul style="list-style-type: none"> 1 Local time 2 UTC time <p>This property is not modifiable.</p>
datetime UntilTime	<p>The time after which the Job is invalid or should be stopped.</p> <p>This may be represented by an actual date and time, or by an interval relative to the time that this property is requested.</p>

	A value of all nines indicates that the Job can run indefinitely.
	This property is not modifiable.
string Notify	User to be notified upon the Job completion or failure.
	This property can be modified using the <i>RequestPropertyChange()</i> method.
string Owner	The User that submitted the Job or the Service/method name/etc. that caused the job to be created.
uint32 Priority	Indicates the urgency or importance of execution of the Job.
	The lower the number, the higher the priority.
	Note that this property is also present in the JobProcessingStatistics class. This is necessary to capture the setting information that would influence a Job's results.
	This property can be modified using the <i>RequestPropertyChange()</i> method.
uint16 PercentComplete	Not supported for z/OS.
boolean DeleteOnCompletion	Indicates whether or not the Job should be automatically deleted upon completion.
	Note that the 'completion' of a recurring Job is defined by its <i>JobRunTimes</i> or <i>UntilTime</i> properties, OR when the Job is terminated by manual intervention.
	If this property is set to false and the Job completes, then the extrinsic method <i>DeleteInstance</i> MUST be used to delete the Job versus updating this property.
	This property is not modifiable.
uint16 ErrorCode	Not supported for z/OS.
string ErrorDescription	Not supported for z/OS.
uint16 RecoveryAction	Not supported for z/OS.
string OtherRecoveryAction	Not supported for z/OS.
string AbendCode	Job completed with abend code.
string AccountNumber	Account number from job card.
boolean ARMRegistered	Job is ARM registered indicator.
string AvailableSchedEnvSystem []	System names onwhich the scheduling environment required by job is available. Only valid if job requires a scheduling environment and that environment is available on at least one system.

string AvailableSeclabelSystems []	System names on which the seclabel associated with the job is available. Only valid if seclabel by system is active in the security product and the seclabel is available on at least on system.
boolean AwaitingARMRestart	Job awaiting ARM restart indicator.
string Building	NJE building. This property is "Expensive".
uint32 CardCount	Card (output) count.
string Class	Job class. This property can be modified using the <i>RequestPropertyChange()</i> method.
uint32 CompletionCode	Completion code (set for conditions marked with + in job completion indicator).
uint8 CompletionType	Specific completion type: 0 No completion info 1 Job ended normally 2 Job ended by CC 3 JCL error 4 Canceled 5 Abended 6 Converter abended 7 Security error 8 Job failed in EOM
uint16 CopyCount	Job copy count. This property is "Expensive".
string CSName	The scoping Computer System.
string DefaultPrintDest	Default print destination. This property can be modified using the <i>RequestPropertyChange()</i> method.
string DefaultPunchDest	Default punch destination. This property can be modified using the <i>RequestPropertyChange()</i> method.
string Department	NJE department. This property is "Expensive".
string Device	Name of device job is active on.
uint32 EstimatedTimeToExecution	Estimated time to execution in seconds. This field is only available if the job is awaiting execution, job is scheduled to run to a WLM managed class, job is not held (duplicate job name, operator hold, etc.), member it has affinity to is available, and the scheduling environment is available.

datetime ExecutionEndTime	Execution end time and date. This property is "Expensive".
string ExecutionMember	Execution JES2 member name. This property is "Expensive".
string ExecutionNode	Execution node. This property can be modified using the <i>RequestPropertyChange()</i> method.
datetime ExecutionStartTime	Execution start time and date. This property is "Expensive".
string ExecutionSystem	Execution MVS system name. This property is "Expensive".
uint8 HoldIndicator	Job hold indicator: 1 Not held 2 Held 3 Held for duplicate job name
uint32 InputCount	Job input count. This property is "Expensive".
string InputDevice	Input device name. This property is "Expensive".
datetime InputStartTime	Input start time and date. This property is "Expensive".
string InputSystem	Input system or member.
boolean JesLogSpinnable	Jeslog spinnable indicator.
boolean JobClassModeWLM	Job class mode for job. If true, mode is WLM, otherwise mode is JES.
string JobID	Job identifier.
boolean JobIsActive	Indicate job is executing.
string JobName	Job name.
uint8 JobType	Job type: 1 Started task (STC) 2 Time sharing user (TSU) 3 Batch job (JOB) 4 APPC indicator
uint32 LineCount	Line count. This property is "Expensive".
string MemberName	JES2 member on which the job is active.
string MessageClass	Message class from job card.
string NotifyNode	Notify node. This property is "Expensive".
string OriginalJobID	Original job identifier.

string OriginNode	Original node (node of submittal).
string OSName	The scoping Operating System's name.
uint32 PageCount	Job page count.
	This property is "Expensive".
uint8 Phase	Phase job is in:
	1 No subchain exists
	2 Active in CI in FSS address space
	3 Awaiting postscan (batch)
	4 Awaiting postscan (damsel)
	5 Awaiting volume fetch
	6 Awaiting start setup (JES3), Awaiting setup (JES2)
	7 Awaiting/active in MDS system select processing
	8 Awaiting resource allocation
	9 Awaiting unavailable volumes
	10 Awaiting volume mounts
	11 Awaiting/active in MDS system verify processing
	12 Error during MDS processing
	13 Awaiting selection on main (JES3), Awaiting execution (JES2)
	14 Scheduled on main (JES3), Active executing (JES2)
	17 Awaiting breakdown (JES3), Active in output (JES2)
	18 Awaiting MDS restart processing
	19 Main MDS processing complete
	20 Awaiting output service (JES3), Awaiting hardcopy (JES2)
	21 Awaiting output service writer
	22 Awaiting reserved services
	23 Output service complete
	24 Awaiting selection on main (demand select job)
	25 Ending function rq waiting or I/O completion
	26 Ending function rq not processed
	27 Maximum rq index value
	128 Active in input processing
	129 Awaiting conversion
	130 Active in conversion
	131 Active in setup
	132 Active in spin
	133 Awaiting output
	134 Awaiting purge
	135 Active in purge
	136 Active on NJE sysout received
	137 Awaiting NJE transmission
	138 Active on NJE job transmitter
string ProgrammerName	Programmer name from job card.
string RoomNumber	Job card room number.

string Seclabel	Seclabel from job.
boolean Spin	Indicator of whether jobs in the job class can be spun.
string Subsystem	Subsystem name.
string SystemName	MVS system name on which the job is active.
uint32 WLMActiveJobCount	Number of active jobs in this WLM service class.
uint32 WLMJobsOnQueueCount	Number of jobs on WLM service class queue.
uint32 WLMPosition	Position of this job on WLM service class queue.
uint32 WLMschedulingEnvironment	WLM scheduling environment. This property can be modified using the <i>RequestPropertyChange()</i> method.
string WLMServiceClass	WLM service class. This property can be modified using the <i>RequestPropertyChange()</i> method.
string PercentSpoolUtilization	Percent of spool Used by the following CIM profiles the job.
boolean ConverterWait	Job can be converted only by CNVT PCEs that can wait for OS
boolean Independent	Job is set to independent mode.
uint32 JobKey	Job key
boolean JobNotRunReasonJobBusyOnDevice	Job not running because job busy on device
boolean JobNotRunReasonJobClassHeld	Job not running because job class held
boolean JobNotRunReasonJobClassLimitReached	Job not running because job class limit reached
boolean JobNotRunReasonNoSystem	Job not running because no system with right combination of resources
boolean JobNotRunReasonSchedulingEnvironment	Job not running due to unavailable scheduling environment
boolean JobNotRunReasonSeclabelAffinity	Job not running because of seclabel affinity
boolean JobNotRunReasonSpoolNotAvailable	Job not running because spools not available
boolean JobNotRunReasonSystemAffinity	Job not running due to system affinity
boolean Protected	Job is protected
uint32 SpoolDataToken	Spool data token

string SystemAffinity []	System affinity for job
boolean SystemDataSet	Job represents a system data set
uint32 TrackGroupCount	Number of track groups of spool space used by this job

Methods

Method	Description	
sint32 Hold()	Holds a job.	
	Parameters	Description
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.
sint32 Release()	Releases a job.	
	Parameters	Description
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.
sint32 ReleaseOutput()	Releases output for a job.	
	Parameters	Description
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.

Method	Description	
sint32 RequestPropertyChange()	Changes a property and returns response messages from the generated command.	
	Parameters	Description
	[IN] string PropertyName	The property to be changed.
	[IN] string PropertyValue	The new value for the property.
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.
sint32 Restart()	Restarts a job.	
	Parameters	Description
	[IN] boolean Hold	Indicates if the job should be held prior to its execution.
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.
sint32 Cancel()	Cancels a job.	
	Parameters	Description
	[IN] boolean PurgeOutput	Indicates if any output associated with the job is to be cancelled.
	[IN] boolean TakeDump	Indicates if a dump should be taken when the job is canceled.
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.

IBMzOS_JES3Job

Purpose

This class is a subclass of IBMzOS_Job and contains those properties that are unique to a job that has run, or will run, under JES3.

Inheritance

IBMzOS_Job
← IBMzOS_JES3Job

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_JES3JobProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_JES3JobProvider.so

Properties

The following properties have been implemented for z/OS:

string Caption	A short description of the class																																
string Description	A description of the class																																
string ElementName	Name of given to this instance of the class																																
datetime InstallDate	Not supported for z/OS.																																
string Name	The property is overridden by <i>IBMzOS_JES3Job</i> . It contains a unique identifier for this Job.																																
uint16 OperationalStatus []	The current status of the JES3 Job: <table><tr><td>1</td><td>No subchain exists</td></tr><tr><td>2</td><td>Active in CI in FSS address space</td></tr><tr><td>3</td><td>Awaiting postscan (batch)</td></tr><tr><td>4</td><td>Awaiting postscan (damsel)</td></tr><tr><td>5</td><td>Awaiting volume fetch</td></tr><tr><td>6</td><td>Awaiting start setup (JES3), Awaiting setup (JES2)</td></tr><tr><td>7</td><td>Awaiting/active in MDS system select processing</td></tr><tr><td>8</td><td>Awaiting resource allocation</td></tr><tr><td>9</td><td>Awaiting unavailable volumes</td></tr><tr><td>10</td><td>Awaiting volume mounts</td></tr><tr><td>11</td><td>Awaiting/active in MDS system verify processing</td></tr><tr><td>12</td><td>Error during MDS processing</td></tr><tr><td>13</td><td>Awaiting selection on main (JES3), Awaiting execution (JES2)</td></tr><tr><td>14</td><td>Scheduled on main (JES3), Active executing (JES2)</td></tr><tr><td>17</td><td>Awaiting breakdown (JES3), Active in output (JES2)</td></tr><tr><td>18</td><td>Awaiting MDS restart processing</td></tr></table>	1	No subchain exists	2	Active in CI in FSS address space	3	Awaiting postscan (batch)	4	Awaiting postscan (damsel)	5	Awaiting volume fetch	6	Awaiting start setup (JES3), Awaiting setup (JES2)	7	Awaiting/active in MDS system select processing	8	Awaiting resource allocation	9	Awaiting unavailable volumes	10	Awaiting volume mounts	11	Awaiting/active in MDS system verify processing	12	Error during MDS processing	13	Awaiting selection on main (JES3), Awaiting execution (JES2)	14	Scheduled on main (JES3), Active executing (JES2)	17	Awaiting breakdown (JES3), Active in output (JES2)	18	Awaiting MDS restart processing
1	No subchain exists																																
2	Active in CI in FSS address space																																
3	Awaiting postscan (batch)																																
4	Awaiting postscan (damsel)																																
5	Awaiting volume fetch																																
6	Awaiting start setup (JES3), Awaiting setup (JES2)																																
7	Awaiting/active in MDS system select processing																																
8	Awaiting resource allocation																																
9	Awaiting unavailable volumes																																
10	Awaiting volume mounts																																
11	Awaiting/active in MDS system verify processing																																
12	Error during MDS processing																																
13	Awaiting selection on main (JES3), Awaiting execution (JES2)																																
14	Scheduled on main (JES3), Active executing (JES2)																																
17	Awaiting breakdown (JES3), Active in output (JES2)																																
18	Awaiting MDS restart processing																																

	19	Main MDS processing complete
	20	Awaiting output service (JES3), Awaiting hardcopy (JES2)
	21	Awaiting output service writer
	22	Awaiting reserved services
	23	Output service complete
	24	Awaiting selection on main (demand select job)
	25	Ending function rq waiting or I/O completion
	26	Ending function rq not processed
	27	Maximum rq index value
	128	Active in input processing
	129	Awaiting conversion
	130	Active in conversion
	131	Active in setup
	132	Active in spin
	133	Awaiting output
	134	Awaiting purge
	135	Active in purge
	136	Active on NJE sysout received
	137	Awaiting NJE transmission
	138	Active on NJE job transmitter
string StatusDescriptions []		Strings describing the various Operational Status values.
string Status		Not supported for z/OS.
string JobStatus		A free form string representing the Job's status. The primary status is reflected in the inherited <i>OperationStatus</i> property. JobStatus provides additional implementation-specific details.
datetime TimeSubmitted		The time that the Job was submitted to execute. A value of all zeros indicates that the owning element is not capable of reporting a date and time. Therefore, the <i>ScheduledStartTime</i> and <i>StartTime</i> are reported as intervals relative to the time their values are required.
datetime ScheduledStartTime		Not supported for z/OS.
datetime StartTime		The time that the Job was actually started. This may be represented by an actual date and time, or by an interval relative to the time that this property is requested. Note that this property is also present in the JobProcessingStatistics class. This is necessary to capture the processing information for recurring Jobs, since only the 'last' run time can be stored in this single-valued property.
datetime ElapsedTime		The time interval that the Job has been executing or the total execution time if the Job is complete.

	<p>Note that this property is also present in the <code>JobProcessingStatistics</code> class. This is necessary to capture the processing information for recurring Jobs, since only the 'last' run time can be stored in this single-valued property.</p>
uint32 JobRunTimes	<p>Number of times that the Job should be run.</p> <p>A value of 1 indicates that the Job is NOT recurring, while any non-zero value indicates a limit to the number of time that the Job will recur.</p> <p>Zero indicates that there is no limit to the number of times that the Job can be processed, but that it is terminated either AFTER the <i>UntilTime</i>, or by manual intervention.</p> <p>By default, a Job is processed once.</p> <p>This property is not modifiable.</p>
uint8 RunMonth	Not supported for z/OS.
sint8 RunDay	Not supported for z/OS.
sint8 RunDayOfWeek	Not supported for z/OS.
datetime RunStartInterval	<p>The time interval after midnight when the Job should be processed.</p> <p>For example, 00000000020000.000000:000 indicates that the Job should be run on of after two o'clock, local time of UTC time (distinguished using the <i>LocalOrUtcTime</i> property).</p> <p>This property is not modifiable.</p>
uint16 LocalOrUtcTime	<p>This property indicates whether the time represented in the <i>RunStartInterval</i> and <i>UntilTime</i> properties represent local or UTC times.</p> <p>Time values are synchronized worldwide by using the enumeration value 2, "UTC Time". Permitted values are:</p> <ul style="list-style-type: none"> 1 Local time 2 UTC time <p>This property is not modifiable.</p>
datetime UntilTime	<p>The time after which the Job is invalid or should be stopped. This may be represented by an actual date and time, or by an interval relative to the time that this property is requested. A value of all nines indicates that the Job can run indefinitely.</p> <p>This property is not modifiable.</p>
string Notify	<p>User to be notified upon the Job completion or failure.</p> <p>This property can be modified using the <i>RequestPropertyChange()</i> method.</p>

string Owner	The User that submitted the Job or the Service/method name/etc. that caused the job to be created.
uint32 Priority	<p>Indicates the urgency or importance of execution of the Job. The lower the number, the higher the priority. Note that this property is also present in the JobProcessingStatistics class. This is necessary to capture the setting information that would influence a Job's results.</p> <p>This property can be modified using the <i>RequestPropertyChange()</i> method.</p>
uint16 PercentComplete	Not supported for z/OS.
boolean DeleteOnCompletion	<p>Indicates whether or not the Job should be automatically deleted upon completion.</p> <p>Note that the 'completion' of a recurring Job is defined by its <i>JobRunTimes</i> or <i>UntilTime</i> properties, OR when the Job is terminated by manual intervention.</p> <p>If this property is set to false and the Job completes, then the extrinsic method <i>DeleteInstance</i> MUST be used to delete the Job versus updating this property.</p> <p>This property is not modifiable.</p>
uint16 ErrorCode	Not supported for z/OS.
string ErrorDescription	Not supported for z/OS.
uint16 RecoveryAction	Not supported for z/OS.
string OtherRecoveryAction	Not supported for z/OS.
string AbendCode	Job completed with abend code.
string AccountNumber	Account number from job card.
boolean ARMRegistered	Job is ARM registered indicator.
string AvailableSchedEnvSystems []	System names on which the scheduling environment required by job is available. Only valid if job requires a scheduling environment and that environment is available on at least one system.
string AvailableSeclabelSystems []	System names on which the seclabel associated with the job is available. Only valid if seclabel by system is active in the security product and the seclabel is available on at least on system.
boolean AwaitingARMRestart	Job awaiting ARM restart indicator.
string Building	<p>NJE building.</p> <p>This property is "Expensive".</p>

uint32 CardCount	Card (output) count.
string Class	Job class. This property can be modified using the <i>RequestPropertyChange()</i> method.
uint32 CompletionCode	Completion code (set for conditions marked with + in job completion indicator).
uint8 CompletionType	Specific completion type: 0 No completion info 1 Job ended normally 2 Job ended by CC 3 JCL error 4 Canceled 5 Abended 6 Converter abended 7 Security error 8 Job failed in EOM
uint16 CopyCount	Job copy count. This property is "Expensive".
string CSName	The scoping Computer System.
string DefaultPrintDest	Default print destination. This property can be modified using the <i>RequestPropertyChange()</i> method.
string DefaultPunchDest	Default punch destination. This property can be modified using the <i>RequestPropertyChange()</i> method.
string Department	NJE department. This property is "Expensive".
string Device	Name of device job is active on.
uint32 EstimatedTimeToExecution	Estimated time to execution in seconds. This field is only available if the job is awaiting execution, job is scheduled to run to a WLM managed class, job is not held (duplicate job name, operator hold, etc.), member it has affinity to is available, and the scheduling environment is available.
datetime ExecutionEndTime	Execution end time and date. This property is "Expensive".
string ExecutionMember	Execution JES2 member name. This property is "Expensive".
string ExecutionNode	Execution node. This property can be modified using the <i>RequestPropertyChange()</i> method.
datetime ExecutionStartTime	Execution start time and date. This property is "Expensive".

string ExecutionSystem	Execution MVS system name. This property is "Expensive".
uint8 HoldIndicator	Job hold indicator: 1 Not held 2 Held 3 Held for duplicate job name
uint32 InputCount	Job input count. This property is "Expensive".
string InputDevice	Input device name. This property is "Expensive".
datetime InputStartTime	Input start time and date. This property is "Expensive".
string InputSystem	Input system or member.
boolean JesLogSpinnable	Jeslog spinnable indicator.
boolean JobClassModeWLM	Job class mode for job. If true, mode is WLM, otherwise mode is JES.
string JobID	Job identifier.
boolean JobIsActive	Indicate job is executing.
string JobName	Job name.
uint8 JobType	Job type: 1 Started task (STC) 2 Time sharing user (TSU) 3 Batch job (JOB) 4 APPC indicator"
uint32 LineCount	Line count. This property is "Expensive".
string MemberName	JES2 member on which the job is active.
string MessageClass	Message class from job card.
string NotifyUserId	Notify user ID.
string OriginalJobID	Original job identifier.
string OriginNode	Original node (node of submittal).
string OSName	The scoping Operating System's name.
uint32 PageCount	Job page count. This property is "Expensive".
uint8 Phase	Phase, the job is in. For the values and their meanings, see property <i>OperationalStatus</i> .
string ProgrammerName	Programmer name from job card.
string RoomNumber	Job card room number.
string Seclabel	Seclabel from job.
boolean Spin	Indicator of whether jobs in the job class can be spun.

string Subsystem Subsystem name.

string SystemName MVS system name on which the job is active.

uint32 WLMActiveJobCount Number of active jobs in this WLM service class.

uint32 WLMJobsOnQueueCount Number of jobs on WLM service class queue.

uint32 WLMPosition Position of this job on WLM service class queue.

uint32 WLMschedulingEnvironment WLM scheduling environment.
This property can be modified using the *RequestPropertyChange()* method.

string WLMServiceClass WLM service class.
This property can be modified using the *RequestPropertyChange()* method.

string PercentSpoolUtilization Percent of spool used by the job.

uint8 JobNotRunReasonCodes [] List or reasons by system for why job is waiting to run

string JobNotRunSystems [] List of system names corresponding to JobNotRunReasonCodes

Methods

Method	Description	
sint32 Hold()[OUT]	Holds a job.	
	Parameters	Description
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.
sint32 Release()	Releases a job.	
	Parameters	Description
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.

Method	Description	
sint32 ReleaseOutput()	Releases output for a job.	
	Parameters	Description
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.
sint32 RequestPropertyChange()	Changes a property and returns response messages from the generated command.	
	Parameters	Description
	[IN] string PropertyName	The property to be changed.
	[IN] string PropertyValue	The new value for the property.
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.
sint32 Restart()	Restarts a job.	
	Parameters	Description
	[IN] boolean Hold	Indicates if the job should be held prior to its execution.
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.

Method	Description	
sint32 Cancel()	Cancels a job.	
	Parameters	Description
	[IN] boolean PurgeOutput	Indicates if any output associated with the job is to be cancelled.
	[IN] boolean TakeDump	Indicates if a dump should be taken when the job is canceled.
	[IN] datetime TimeoutPeriod	Specifies the maximum amount of time that the client expects the transition to the new state to take.
	[OUT] string ResponseText[]	Command response messages.
	[OUT] sint32 ReasonCode	Reason code referencing CEA errors.

IBMzOS_JES2SysoutDataset

Purpose

This class is a subclass of IBMzOS_SysoutDataset and contains those properties that are unique to a job that has run under JES2.

Inheritance

IBMzOS_SysoutDataset
← IBMzOS_JES2SysoutDataset

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_JES2SysoutDatasetProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_JES2SysoutDatasetProvider.so

Properties

string Caption	A short description of the class
string Description	A description of the class
string ElementName	Name of given to this instance of the class
datetime InstallDate	Not supported for z/OS.
string Name [key]	JES2 Sysout Dataset name
uint16 OperationalStatus []	The current status of the JES2SysoutDataset: 0 = Unknown 2 = OK 6 = Error 9 = Stopping
string StatusDescriptions []	Not supported for z/OS.
string Status	Not supported for z/OS.
string CSCreationClassName [key]	The scoping ComputerSystem's CreationClassName.
string CSName [key]	The scoping ComputerSystem's Name.
string FSCreationClassName [key]	The scoping FileSystem's CreationClassName.
string FSName [key]	The scoping FileSystem's Name.
string CreationClassName [key]	Indicates the name of the class or the subclass used in the creation of an instance. When used with the other key properties of this class, this property allows all instances of this class and its subclasses to be uniquely identified.

uint64 FileSize	Not supported for z/OS.
datetime CreationDate	Not supported for z/OS.
datetime LastModified	Not supported for z/OS.
datetime LastAccessed	Not supported for z/OS.
boolean Readable	Boolean indicating that the File can be read.
boolean Writeable	Boolean indicating the File can be written.
boolean Executable	Boolean indicating the File is executable.
string CompressionMethod	Not supported for z/OS.
string EncryptionMethod	Not supported for z/OS.
uint64 InUseCount	Not supported for z/OS.
string ActiveMember	The JES member on which the sysout is active
string ActiveSysname	z/OS system on which the sysout is active
boolean Burst	Indicates whether 'Burst' mode is supported.
uint64 ByteCount	Byte count after blank truncation
string Class	The sysout class
datetime CreateTime	Date and time the data set became available This property is "Expensive".
string DataSetName	Sysout data set name This property is "Expensive".
uint32 DataSetNumber	Data set number This property is "Expensive".
string DDName	DDName for the data set creation This property is "Expensive".
string Destination	Sysout destination
string DeviceName	Name of the device on which sysout is active
string FCB	The name of the File Control Block (FCB) associated with this dataset.
boolean HeldByOperator	Sysout is held due to operator command
boolean HeldBySystem	Sysout is in a system hold
boolean HeldByUser	Sysout is currently held
string Identifier	This identifier is a value associated with this sysout that can be used in operator commands. The exact contents vary based on whether JES2 or JES3 owns the sysout and the release of JES processing the SSI request.
boolean IPAddrDest	Indicates that the 'Destination' property contains an Internet Protocol (IP) address.
string JobID	Job identified
string Jobname	Job name

uint16 MaxLogicalRecordLength	Maximum logical record length This property is "Expensive".
string ModifyModname	Modify=(modname)
string ModifyTrc	Modify=(,trc)
boolean NotSelectable	Not selectable
string OutDisp	Output disposition
string Owner	Sysout owner
uint32 PageCount	Page count
uint8 Priority	Sysout priority
string ProcessMode	Processing mode
string ProcName	Procname for the step creating this data set
uint32 RecordCount	Record count
string RecordFormat	Record format This property is "Expensive".
string Seclabel	Seclabel for sysput
uint32 SegmentID	Segment ID (zero if data set is not segmented)
boolean Spin	Spin data set
string StepName	Stepname for the step creating this data set This property is "Expensive".
string Subsystem	Subsystem name
string SystemHoldReason	Reason for system hold
string TPJobName	APPC transaction program jobname that created this data set
string TranslateTable []	Printer translate table
string UCS	UCS
string WriterName	External writer name
string JobToken	Job token
string OutputGroupElement	Sysout group name
datetime OutputGroupElementCreateTime	JOE creation time
uint16 OGID1	JOE ID1
string Forms	specifies the forms on which the data set is to be printed
string Flash	specifies the form overlay

IBMzOS_JES3SysoutDataset

Purpose

This class is a subclass of IBMzOS_SysoutDataset and contains those properties that are unique to a job that has run under JES3.

Inheritance

IBMzOS_SysoutDataset
← IBMzOS_JES3SysoutDataset

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_JES3SysoutDatasetProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_JES3SysoutDatasetProvider.so

Properties

The properties of IBMzOS_JES3SysoutDataset are the same as for IBMzOS_JES2SysoutDataset (see “IBMzOS_JES2SysoutDataset” on page 180 with some exceptions:

IBMzOS_JES3SysoutDataset does not provide the following properties of IBMzOS_JES2SysoutDataset:

- OutputGroupElement
- OutputGroupElementCreateTime
- OGID1

The following properties are only part of IBMzOS_JES3SysoutDataset:

boolean HeldForTSO Sysout is held for TSO

boolean HeldForExternalWriter
Sysout is held for external writer

IBMzOS_Job

Purpose

This class represents a z/OS job. Jobs are associated with a subsystem, such as JES2, JES3, or MSTR. Some properties may require significant overhead, including I/O, to obtain their data. These properties are identified with the qualifier of "Expensive". To reduce system overhead, the provider will only return the values for these expensive properties if they are explicitly requested by name.

Inheritance

Subclasses are IBMzOS_JES2Job (see "IBMzOS_JES2Job" on page 161) and IBMzOS_JES3Job (see "IBMzOS_JES3Job" on page 171).

IBMzOS_JobsManagementSettings

Purpose

The IBMzOS_JobsManagementSettings class provides a mechanism by which users can influence the behavior of the IBMzOS_JES2SysoutDataset, IBMzOS_JES3SysoutDataset, IBMzOS_JES2Jobs, and IBMzOS_JES3Jobs providers.

Properties

string Caption	A short description of the class
string Description	A description of the class
string ElementName	Name given to this instance of the class
string InstanceID [Key]	<p>Within the scope of the instantiating Namespace, <i>InstanceID</i> opaquely and uniquely identifies an instance of this class. In order to ensure uniqueness within the Namespace, the value of InstanceID SHOULD be constructed using the following algorithm:</p> <p><OrgID>:<LocalID></p> <p>where <OrgID> and <LocalID> are separated by a colon ':', and where <OrgID> MUST include a copyrighted, trademarked or otherwise unique name that is owned by the business entity creating/defining the InstanceID, or is a recognized global authority (This is similar to the <Schema Name>_<Class Name> structure of Schema class names.) In addition, to ensure uniqueness <OrgID> MUST NOT contain a colon (':'). When using this algorithm, the first colon in InstanceID MUST be between <OrgID> and <LocalID>.</p> <p><LocalID> is chosen by the business entity and SHOULD not be re-used to identify different underlying (real-world) elements. If the above 'preferred' algorithm is not used, the defining entity MUST assure that the resultant InstanceID is not re-used across any InstanceIDs produced by this or other providers for this instance's Namespace.</p> <p>For DMTF defined instances, the 'preferred' algorithm MUST be used with the <OrgID> set to 'CIM'.</p>
uint32 MaxInstances	The maximum number of instances that can be returned.
uint32 MaxProperties	The maximum number of properties that can be returned

IBMzOS_Subsystem

Purpose

This class represents a z/OS Subsystem.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SubsystemProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SubsystemProvider.so

Properties

string Caption	A short description of the class
string Description	A description of the class
string ElementName	Name given to this instance of the class
datetime InstallDate	Not supported for z/OS.
string Name [key]	Subsystem name
uint16 OperationalStatus []	The current status of the JobSubSystem: 0 Unknown 2 OK 6 Error 9 Stopping
string StatusDescriptions []	Strings describing the various Operational Status values.
string Status	Not supported for z/OS.
uint16 EnabledState	Indicates the Enabled or Disabled state.
string OtherEnabledState	String describing the Enabled State value.
uint16 RequestedState	The last requested State.
uint16 EnabledDefault	Indicates the default value for Enabled State.
datetime TimeOfLastStateChange	Not supported for z/OS.
string SystemCreationClassName [key]	The scoping System's CreationClassName.
string SystemName [key]	The scoping System's Name.
string CreationClassName [key]	Indicates the name of the class or the subclass used in the creation of an instance. When used with the other key properties of this class, this property allows all instances of this class and its subclasses to be uniquely identified.
string PrimaryOwnerName	Not supported for z/OS.
string PrimaryOwnerContact	Not supported for z/OS.

string StartMode	StartMode is a string value indicating whether the Service is automatically started by a System, Operating System, etc. or only started upon request. This property is deprecated. Use the EnabledDefault property inherited from EnabledLogicalElement instead.						
boolean Started	True if subsystem is active.						
boolean Dynamic	True is subsystem is dynamic.						
boolean DynamicCommands	True if subsystem responds to SETSSI command.						
boolean Primary	Indicator for primary subsystem						
uint8 Type	Subsystem type code: <table> <tr> <td>1</td><td>Unknown</td></tr> <tr> <td>2</td><td>JES2</td></tr> <tr> <td>3</td><td>JES3</td></tr> </table>	1	Unknown	2	JES2	3	JES3
1	Unknown						
2	JES2						
3	JES3						

IBMzOS_SysoutDataset

Purpose

This class represents a z/OS sysout dataset. Some properties may require significant overhead, including I/O, to obtain their data. These properties are identified with the qualifier of "Expensive". To reduce system overhead, the provider will only return the values for these expensive properties if they are explicitly requested by name.

Inheritance

Subclasses are

- IBMzOS_JES2SysoutDataset (see “IBMzOS_JES2SysoutDataset” on page 180) and
- IBMzOS_JES3SysoutDataset (see “IBMzOS_JES3SysoutDataset” on page 183).

Association IBMzOS_SubsystemJES2Jobs

Purpose

This class associates an IBMzOS_Subsystem with an IBMzOS_JES2Job.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SubsystemJES2JobsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SubsystemJES2JobsProvider.so

Association IBMzOS_SubsystemJES3Jobs

Purpose

This class associates an IBMzOS_Subsystem with an IBMzOS_JES3Job.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SubsystemJES3JobsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SubsystemJES3JobsProvider.so

Association IBMzOS_UsesJES2SysoutDatasets

Purpose

This class associates an IBMzOS_JES2Job with an IBMzOS_JES2SysoutDataset.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_UsesJES2SysoutDatasetsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_UsesJES2SysoutDatasetsProvider.so

Association IBMzOS_UsesJES3SysoutDatasets

Purpose

This class associates an IBMzOS_JES3Job with an IBMzOS_JES3SysoutDataset.

| **Module name**

| The module name of the CMPI provider that is registered for a CIM class which is
| used by the cimprovider command line tool for the administration of CMPI
| providers is

| IBMzOS_UsesJES3SysoutDatasetsProviderModule

| **Provider library**

| The physical name of a CMPI provider's shared object library as it is stored in the
| hierarchical file system is

| libcmpiIBMzOS_UsesJES3SysoutDatasetsProvider.so

OS management Cluster classes

The classes described in this section are implemented by z/OS to instrument the z/OS "Systems Complex" (Sysplex) clustering facility.

For using these providers you need an extra security setup as described in "Setting up the CIM server for Cluster, CoupleDataset, and JES2-JES3Jobs providers" on page 38.

IBMzOS_CFRMCoupleDataset

Purpose

This class represents Coupling Facility Resource Manager (CFRM) couple datasets. A CFRM couple dataset contains CFRM policies, one of which can be active (started), defining how z/OS manages coupling facility resources.

A CFRM couple dataset can be the active primary, or optionally, the active alternate couple dataset supporting the CFRM coupling function. Minimally, a CFRM couple dataset must be in use as the active primary CFRM couple dataset for CFRM coupling function to be active.

Inheritance

IBMzOS_CoupleDataset
← IBMzOS_CFRMCoupleDataset

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CFRMCoupleDatasetProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CFRMCoupleDatasetProvider.so

Properties

string Name	The name of the couple dataset represented by an instance of this class.
uint32 NumberOfStructures	<p>The number of coupling facility (CF) structures that the CFRM couple dataset is formatted to support.</p> <p>It is the maximum number of structures that can be defined for use in a policy contained in this couple dataset.</p>
uint32 NumberOfConnectors	<p>Identifies the number of connectors per structure that the couple dataset is formatted to support.</p> <p>Connectors are programs running under z/OS that establish a connection to a CF structure. It is the maximum number of concurrent connectors that can be supported for each structure defined in the couple dataset.</p>
uint32 NumberOfCFs	<p>The number of coupling facilities the couple dataset is formatted to support.</p> <p>It is the maximum number of CFs that can be defined for use in a CFRM policy contained in this couple dataset.</p>
uint32 NumberOfPolicies	The number of administrative (inactive) policies that the couple dataset is formatted to support.
boolean SystemManagedDuplexing	Indicates whether or not the couple dataset is

formatted to support the use of the system-managed duplexing rebuild process.

System-managed duplexing rebuild is a process managed by z/OS that allows a structure to be maintained as a duplexed pair. The process is controlled by CFRM policy definitions as well as by the program owning the structure. The process can be initiated via operator command (SETXCF), programming interface (IXLREBLD), or can be z/OS-initiated. Note that user-managed duplexing rebuild is controlled and initiated in the same manner as system-managed duplexing rebuild, but is managed by the program owning the structure and applies only to cache structures.

boolean SystemManagedRebuild

Indicates whether or not the couple dataset is formatted to support the use of the system-managed structure rebuild process.

System-managed structure rebuild is a process managed by z/OS that allows a structure to be rebuilt by z/OS. The process is controlled by CFRM policy definitions as well as by the program owning the structure. The process can be initiated via operator command (SETXCF), programming interface (IXLREBLD), or can be z/OS-initiated. Note that user-managed structure rebuild is controlled and initiated in the same manner as system-managed rebuild, but is managed by the program owning the structure and applies only to cache structures.

boolean MessageBased

Indicates whether or not the couple dataset is formatted to support the use of message-based CFRM event notification and confirmation capabilities.

IBMzOS_CFRMPolicy

Purpose

This class represents administrative (inactive) Coupling Facility Resource Manager (CFRM) policies. CFRM policies are used to control Coupling Facility (CF) and CF structure resources available to a z/OS Sysplex (Systems Complex). There can be only one active CFRM policy and some number of administrative (inactive) policies.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CFRMPolicyProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CFRMPolicyProvider.so

Properties

string Caption	A short description of the class.
string Description	A description of the class.
string ElementName	Name given to this instance of the class.
datetime InstallDate	A datetime value indicating when the object was installed. A lack of a value does not indicate that the object is not installed.
string Name [key]	Name of CFRM Policy
uint16 OperationalStatus []	The current status of the SysplexCoupleDataset: 0 = Unknown 2 = OK 6 = Error 9 = Stopping
string StatusDescriptions []	Strings describing the various Operational Status values.
string Status	A string indicating the current status
string EnabledState	Indicates the Enabled or Disabled state.
string OtherEnabledState	String describing the Enabled State value.
uint16 RequestedState	The last requested State.
uint16 EnabledDefault	Indicates the default value for Enabled State.
datetime TimeOfLastStateChange	The date and time Enabled State was last changed.
string PolicyText	This property contains the CFRM policy statements that define the Coupling Facilities (CFs) and CF structures that are eligible to be used by programs operating in the Sysplex when this policy is activated (started) via the <i>StartPolicy()</i> method.

The CFRM policy, as defined by its *PolicyText*, governs many aspects of the use of CFs and CF structures by the Sysplex. For example, it governs CF structure placement, fixing, recovery and availability considerations.

Methods

StartPolicy()

Starts a policy.

StopPolicy()

Stops a policy.

IBMzOS_CFStructure

Purpose

This class represents a zSeries Coupling Facility Structure.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CFStructureProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CFStructureProvider.so

Properties

string Caption	A short description of the class.
string Description	A description of the class.
string ElementName	Name given to this instance of the class.
datetime InstallDate	A datetime value indicating when the object was installed. A lack of a value does not indicate that the object is not installed.
string Name	The Name of the structure as defined in the CFRM policy.
uint16 OperationalStatus []	The current status of the CF Structure: 0 Unknown 2 OK 6 Error 9 Stopping
string StatusDescriptions []	Strings describing the various Operational Status values.
string Status	A string indicating the current status
uint16 EnabledState	Indicates the Enabled or Disabled state.
string OtherEnabledState	String describing the Enabled State value
uint16 RequestedState	The last requested State
uint16 EnabledDefault	Indicates the default value for Enabled State
datetime TimeOfLastStateChange	The date and time Enabled State was last changed.
uint64 IdentityToken [key]	The generated identity value for sysplex cluster. (Part 1 of 2)
string IdentityName [key]	The generated identity value for sysplex cluster. (Part 2 of 2)
uint32 State	CF structure operational state: 1 Okay 2 Unknown 3 Error 4 Stopping

uint32 SubState	<p>CF structure substate:</p> <ol style="list-style-type: none"> 1 Normal (no exceptional conditions). 2 Temporarily degraded (alter in progress, structure dump serialization held). 3 Permanently degraded (allocated smaller than desired size, pending CFRM policy change). 4 Recovering (Valid only when the value of 'State' is 1 (Okay) or 4 (Stopping)).
uint8 Type	<p>Structure type based on exploiter allocation requirements:</p> <p>0x03 List</p> <p>0xFF Lock</p> <p>0x04 Cache</p> <p>0xFE Serialized List</p>
boolean AllowAlter	<p>Indicator of whether this structure can be dynamically altered, based on current conditions. All active connectors to the structure specified ALLOWAUTO = YES on the IXLCONN connect request.</p>
boolean AllowAuto	<p>All active connectors to the structure specified ALLOWREBLD = YES on the IXLCONN connect request.</p>
boolean AllowRebuild	<p>All active connectors to the structure specified ALLOWDUPREBLD = YES on the IXLCONN connect request.</p>
boolean AllowDupRebuild	<p>All active connectors to the structure specified ALLOWALTER = YES on the IXLCONN connect request.</p>
boolean IsDuplexed	<p>Indicator of whether this structure actually is duplexed at this time. Only when this property indicates that the structure is duplexed, will the following properties be valid:</p> <ul style="list-style-type: none"> • MaximumStructureSize2 • InitialStructureSize2 • MinimumStructureSize2 • OverFullThreshold2 • StructureVersion2 • CFName2 • CurrentStructureSize2
boolean PendPolicyChange	<p>Indicates that there is a change pending in structure policy.</p>
boolean Disposition	<p>Defines whether the structure is persistent when there are no longer any defined connections (active or failed):</p> <p>FALSE Keep</p> <p>TRUE Delete</p>
string CFName1	<p>The name of the Coupling Facility in which this structure instance has been allocated.</p>

	<p>It is possible to have two structure instances due to rebuild-in-progress or duplexing.</p> <p>It is possible to have no structure instances when the structure is not currently allocated.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
string CFName2	<p>The name of the Coupling Facility in which the 'New' structure instance has been allocated. Null if not allocated.</p> <p>This property is only valid when Duplexed.</p>
string StructureVersion1	<p>Structure version number for the currently allocated instance of the structure.</p> <p>It is possible to have two structure instances due to rebuild-in-progress or duplexing. It is possible to have no structure instances when the structure is not currently allocated.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
string StructureVersion2	<p>Structure version number for the 'New' instance of the structure, when the structure is in the process of rebuilding or has been duplexed.</p> <p>This property is only valid when Duplexed.</p>
uint32 MaximumStructureSize1	<p>The maximum size to which this instance of the structure can be expanded, in units of 4KB.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint32 MaximumStructureSize2	<p>The maximum size to which the 'New' instance of the structure can be expanded, in units of 4KB.</p> <p>This property is only valid when Duplexed.</p>
uint32 InitialStructureSize1	<p>The requested initial structure allocation size, in units of 4KB, for this instance of the structure.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint32 InitialStructureSize2	<p>The requested initial structure allocation size, in units of 4KB, for the 'New' instance of the structure.</p> <p>This property is only valid when Duplexed.</p>
uint32 MinimumStructureSize1	<p>The minimum size at which this instance of the structure can be allocated or contracted to, in units of 4KB.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>

uint32 MinimumStructureSize2	<p>The minimum size at which the 'New' instance of the structure can be allocated or contracted to, in units of 4KB.</p> <p>This property is only valid when Duplexed.</p>
uint32 CurrentStructureSize1	<p>The allocated structure size, in units of 4 KB, for this instance of the structure. Not provided if the structure is not allocated.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint32 CurrentStructureSize2	<p>The allocated structure size, in units of 4 KB, for the 'New' instance of the structure. Not provided if the structure is not allocated.</p> <p>This property is only valid when Duplexed.</p>
uint32 SysMgdProcessLevel1	<p>System Managed Process Level required by the instance of the structure to participate in a system-managed process.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint32 SysMgdProcessLevel2	<p>System Managed Process Level required by the 'New' instance of the structure to participate in a system-managed process.</p> <p>This property is only valid when Duplexed.</p>
uint32 ElementCount1	<p>Element Count for the structure. List set element count for List structures. Data area element count for Cache Structures. Invalid for Lock Structures.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint32 ElementCount2	<p>Element Count for the 'New' structure. List set element count for List structures. Data area element count for Cache Structures. Invalid for Lock Structures.</p> <p>This property is only valid when Duplexed.</p>
uint32 EntryCount1	<p>Entry Count for the structure. List set entry count for List and Lock Structures. Directory entry count for cache structures.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint32 EntryCount2	<p>Entry Count for the 'New' structure. List set entry count for List and Lock Structures. Directory entry count for cache structures.</p> <p>This property is only valid when Duplexed.</p>
uint32 EMCCount1	<p>Event Monitor Controls count for List Structures. Invalid for Cache structures and Lock structures.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>

uint32 EMCCount2	<p>Event Monitor Controls count for 'New' List Structures. Invalid for Cache structures and Lock structures.</p> <p>This property is only valid when Duplexed.</p>
uint32 LockCount1	<p>Lock Entry Count. Valid for serialized List and Lock Structures. Invalid for Cache Structures and unserialized List structures.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint32 LockCount2	<p>Lock Entry Count. Valid for 'New' serialized List and Lock Structures. Invalid for Cache Structures and unserialized List structures.</p> <p>This property is only valid when Duplexed.</p>
string LogicalVersion1	<p>Logical Version numner for the instance of the structure.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
string LogicalVersion2	<p>Logical Version numner for the 'New' instance of the structure.</p> <p>This property is only valid when Duplexed.</p>
string PreferenceList1 []	<p>Structure Preference List for the instance of the structure. It is an array of up to 8 Coupling Facility names.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
string PreferenceList2 []	<p>Structure Preference List for the instance of the structure. This is an array of up to 8 coupling facility names.</p> <p>This property is only valid when Duplexed.</p>
string ExclusionList1 []	<p>The Structure Exclusion List for the instance of the structure. This is an array of up to 8 coupling facility names.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
string ExclusionList2 []	<p>Structure Exclusion List for the 'New' instance of the structure. This is an array of up to 8 coupling facility names.</p> <p>This property is only valid when Duplexed.</p>
uint32 AccessTimeMax1	<p>This instance of the structure was allocated with access time for IXLCONN ACCESTIME(MAXIMUM).</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>
uint16 AccessTimeMax2	<p>The 'New' instance of the structure was allocated with access time for IXLCONN ACCESTIME(MAXIMUM).</p>

	This property is only valid when Duplexed.
uint16 MaximumConnections1	<p>The maximum number of connections allowed when the structure was allocated in the coupling facility.</p> <p>When Duplexed this is the 'Old' version of the structure.</p>
uint16 MaximumConnections2	<p>The maximum number of connections allowed when the 'New' instance of the structure was allocated in the coupling facility.</p> <p>This property is only valid when Duplexed.</p>
uint8 FullThreshold1	<p>Percentage value for the structure full monitoring threshold for the structure, as defined in CFRM policy. This threshold is set on-platform and is not currently settable through the resource model.</p> <p>When Duplexed this is the 'Old' version of the structure.</p>
uint8 FullThreshold2	<p>Percentage value for the structure full monitoring threshold for the 'New' version of the structure, as defined in CFRM policy. This threshold is set on-platform and is not currently settable through the resource model.</p> <p>This property is only valid when Duplexed.</p>
uint8 RebuildPercent1	<p>REBUILDPERCENT for the instance of the structure as specified in CFRM active policy. Not valid indicates not specified.</p> <p>When Duplexed this is the 'Old' version of the structure.</p>
uint8 RebuildPercent2	<p>REBUILDPERCENT for the 'New' instance of the structure as specified in CFRM active policy. Not valid indicates not specified.</p> <p>This property is only valid when Duplexed.</p>
uint8 DuplexPolicy1	<p>The effective DUPLEX option for the structure as specified in the CFRM active policy or defaulted.</p> <p>When Duplexed this is the 'Old' version of the structure.</p>
uint8 DuplexPolicy2	<p>The effective DUPLEX option for the 'New' structure as specified in the CFRM active policy or defaulted.</p> <p>This property is only valid when Duplexed.</p>
boolean OverFullThreshold1	<p>Indicator of whether or not the instance of the structure is currently in violation of its structure full monitoring threshold.</p> <p>When Duplexed this is the 'Old' instance of the structure.</p>

boolean OverFullThreshold2	Indicator of whether or not the 'New' instance of the structure is currently in violation of its structure full monitoring threshold. This property is only valid when Duplexed.
boolean AllowAutoAlter1	ALLOWAUTOALT(YES) was specified in the CFRM active policy for the structure. When Duplexed this is the 'Old' instance of the structure.
boolean AllowAutoAlter2	ALLOWAUTOALT(YES) was specified in the CFRM active policy for the 'New' structure. This property is only valid when Duplexed.
boolean EnforceOrder1	ENFORCEORDER(YES) was specified in the CFRM active policy for the structure. When Duplexed this is the 'Old' instance of the structure.
boolean EnforceOrder2	ENFORCEORDER(YES) was specified in the CFRM active policy for the 'New' structure. This property is only valid when Duplexed.
boolean AllowReallocate1	ALLOWREALLOCATE(YES) was specified in the CFRM active policy for the structure. When Duplexed this is the 'Old' instance of the structure.
boolean AllowReallocate2	ALLOWREALLOCATE(YES) was specified in the CFRM active policy for the 'New' structure. This property is only valid when Duplexed.
boolean AccessTimeNoLimit1	The instance of the structure was allocated with IXLCONN ACESSTIME(NOLIMIT) When Duplexed this is the 'Old' instance of the structure.
boolean AccessTimeNoLimit2	The 'New' instance of the structure was allocated with IXLCONN ACESSTIME(NOLIMIT). This property is only valid when Duplexed.
uint32 MaxElementCount1	The maximum Element Count for the structure. List set element count for List structures. Data area element count for Cache Structures. Invalid for Lock Structures. When Duplexed this is the 'Old' instance of the structure.
uint32 MaxElementCount2	The maximum Element Count for the 'New' structure. List set element count for List structures. Data area element count for Cache Structures. Invalid for Lock Structures. This property is only valid when Duplexed.
uint32 MaxEntryCount1	The maximum Entry Count for the structure. List

	<p>set entry count for List and Lock Structures. Directory entry count for cache structures.</p> <p>When Duplexed this is the 'Old' instance of the structure</p>
uint32 MaxEntryCount2	<p>The maximum Entry Count for the 'New' structure. List set entry count for List and Lock Structures. Directory entry count for cache structures.</p> <p>This property is only valid when Duplexed.</p>
uint32 MaxEMCCount1	<p>The maximum Event Monitor Controls count for List Structures. Invalid for Cache structures and Lock structures. When Duplexed this is the 'Old' instance of the structure</p>
uint32 MaxEMCCount2	<p>The maximum Event Monitor Controls count for 'New' List Structures. Invalid for Cache structures and Lock structures. This property is only valid when Duplexed.</p>

Methods

uint32 StartRebuild()	<p>Asynchronously rebuilds the structure into the same or a different CF than the one in which it is currently located.</p> <p>Only works if supported by exploiters. The Location parameter specifies the location where the new structure can be built.</p> <p>The LessConnAction parameter indicates whether the rebuild should be allowed to continue, in spite of a degradation in connectivity to the new structure.</p> <p>A rebuild operation should only be requested for structures that are identified as rebuild capable. The rebuild will be performed asynchronously. The return and reason codes will indicate whether the operation was initiated successfully. A property change event will be generated asynchronously when the rebuild has completed.</p> <p>Coupling Facility Structure operations should only be invoked from a single system in the sysplex.</p>
uint32 StopRebuild()	<p>Stops a Rebuild operation.</p> <p>A property change event will be generated when the operation has completed.</p> <p>Coupling Facility Structure Operations should only be invoked from a single system in the sysplex.</p>
uint32 StartDuplex()	<p>Asynchronously establishes duplexing for the specified structure.</p> <p>Only works if supported by exploiters. The request to start duplexing will be performed asynchronously. The return and reason codes will indicate whether the operation was initiated</p>

	successfully. A property change event will be generated asynchronously when the duplexing has completed.
	Coupling Facility Structure Operations should only be invoked from a single system in the sysplex.
uint32 StopDuplex()	<p>Stops duplexing.</p> <p>The required Keep parameter indicates which structure is to persist after duplexing has been stopped. The request to stop duplexing will be performed asynchronously. The return and reason codes will indicate whether the operation was initiated successfully. A property change event will be generated asynchronously when operation has completed.</p> <p>Coupling Facility Structure Operations should only be invoked from a single system in the sysplex.</p>
uint32 Force()	<p>Asynchronously forces the deallocation of a persistent structure.</p> <p>Force of a structure does not work if there are any active connectors to the structure, and may or may not work if there are failed connectors to the structure. The return and reason codes will indicate whether the operation was initiated successfully. CFStructure property change event or life cycle event will be generated asynchronously when the Force operation has completed.</p>
uint32 ForceAll()	<p>Asynchronously forces the deletion of all failed-persistent connections for this structure.</p> <p>The return and reason codes will indicate whether the operation was initiated successfully. Connector life cycle events or relationship-related events will be generated asynchronously when the failed persistent connectors are deleted.</p>

Associations

IBMzOS_CFStrDependsOn

Source	IBMzOS_CFStructure
Target	IBMzOS_CFStructureConnector
see	page 228

Indications

IBMzOS_CFStructureInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStructure class has been created.

IBMzOS_CFStructureInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStructure class has been deleted.

IBMzOS_CFStructureInstModification

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStructure class has been modified.

IBMzOS_CFStructureConnector

Purpose

This class represents a zSeries Coupling Facility Structure Connector.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CFStructureConnectorProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CFStructureConnectorProvider.so

Properties

string Caption	A short description of the class.
string Description	A description of the class.
string ElementName	Name given to this instance of the class.
datetime InstallDate	A datetime value indicating when the object was installed. A lack of a value does not indicate that the object is not installed.
string Name	The Connector name.
uint16 OperationalStatus []	The current status of the CF connector: 0 Unknown 2 OK 6 Error 9 Stopping
string StatusDescriptions []	Strings describing the various Operational Status values.
string Status	A string indicating the current status
uint16 EnabledState	Indicates the Enabled or Disabled state.
string OtherEnabledState	String describing the Enabled State value
uint16 RequestedState	The last requested State
uint16 EnabledDefault	Indicates the default value for Enabled State
datetime TimeOfLastStateChange	The date and time Enabled State was last changed.
uint64 IdentityToken [key]	The generated identity value for sysplex cluster. (Part 1 of 2)
string IdentityName [key]	The generated identity value for sysplex cluster. (Part 2 of 2)
string ConnectorStructureName	The CFStructure name for the connection.
string ConnectorSystemName	OperatingSystem name for the system where the connector is running.

string ConnectorProcessName	Process name for the process in which the connector is running (for z/OS this is a jobname).
string ConnectorProcessID []	Unique process identification for the process in which the connector is running (for z/OS this is a token).
uint32 State	Operational state of the CF connector: 0 Okay 2 Unknown 6 Error 9 Stopping
string ConnectorLevel	Connector-specified level information, or 0 if not provided by the connector.
boolean FailureIsolation	Indicator of whether or not the structure as currently allocated satisfies this connector's requirements for failure-isolation.
boolean Disposition	Indicator of the connector disposition. Defines whether the connection is persistent if the connection abnormally terminates. FALSE Delete TRUE Keep
boolean NonVolatileRequest	Indicator of whether the connector requested non-volatility.
string ConnectorIdentifier	Connector Identifier.
string ConnectorVersion	Connector version number.
string ConnectorData	Connector data.
uint8 ConnectorInfoLevel	Connector Level of information.
uint8 ConnectorCFLevelRequired	Connector CF Level required.
boolean AllowRebuild	Indicates that the connector was connected with ALLOWREBUILD = YES
boolean AllowDupRebuild	Indicates that the connector was connected with ALLOWDUPBUILD = YES
boolean AllowAuto	Indicates that the connector was connected with ALLOWAUTO = YES
boolean AllowAlter	Indicates that the connector was connected with ALLOWALTER = YES
boolean Suspend	Indicates that the connector was connected with ALLOWALTER = YES, SUSPEND = YES
boolean AllowRatio	Indicates that the connector was connected with ALLOWALTER = YES, RATIO = YES
uint8 MinEntry	Indicates the value the connector specified for MINENTRY
uint8 MinElement	Indicates the value the connector specified for MINELEMENT
uint8 MinEMC	Indicates the value the connector specified for MINEMC

Methods

uint32 Force()

Asynchronously forces deletion of a failed connector to a structure, following a failure.

For some structures this is not permitted unless the structure itself is also forced (deallocated). This operation can only be performed against a structure connector in the ERROR state. The return and reason codes will indicate whether the operation was initiated successfully. Structure connector property change events or life cycle events will be generated asynchronously when the force operation has completed.

Indications

IBMzOS_CFStrConnectorInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStrConnector class has been created.

IBMzOS_CFStrConnectorInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStrConnector class has been deleted.

IBMzOS_CFStrConnectorInstModification

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStrConnector class has been modified.

IBMzOS_CoupleDataset

Purpose

This class represents the methods and properties common to all specific types of z/OS couple datasets. Examples of z/OS couple datasets include z/OS System Complex (Sysplex) and Coupling Facility Resource Manager (CFRM) couple datasets.

Inheritance

Subclasses are

- IBMzOS_SysplexCoupleDataset (see “IBMzOS_SysplexCoupleDataset” on page 224) and
- IBMzOS_CFRMCoupleDataset (see “IBMzOS_CFRMCoupleDataset” on page 192).

Properties

string Caption	A short description of the class.
string Description	A description of the class.
string ElementName	Name given to this instance of the class.
datetime InstallDate	Not supported for z/OS.
string Name [key]	Name of Couple Dataset
uint16 OperationalStatus []	The current status of the SysplexCoupleDataset: 0 = Unknown 2 = OK 6 = Error 9 = Stopping
string StatusDescriptions []	Strings describing the various Operational Status values.
string Status	Not supported for z/OS.
string CSCreationClassName [key]	The scoping ComputerSystem's CreationClassName.
string CSName [key]	The scoping ComputerSystem's Name.
string FSCreationClassName [key]	The scoping FileSystem's CreationClassName.
string FSName [key]	The scoping FileSystem's name.
string CreationClassName [key]	CreationClassName indicates the name of the class or the subclass used in the creation of an instance. When used with the other key properties of this class, this property allows all instances of this class and its subclasses to be uniquely identified.
uint64 FileSize	Not supported for z/OS.
datetime CreationDate	Not supported for z/OS.
datetime LastModified	Not supported for z/OS.
datetime LastAccessed	Not supported for z/OS.

boolean Executable	Indicates that the File is executable.
string CompressionMethod	Not supported for z/OS.
string EncryptionMethod	Not supported for z/OS.
uint64 InUseCount	Not supported for z/OS.
string SysplexName	<p>This is the name of the z/OS Sysplex to which the couple dataset represented by an instance of this class belongs.</p> <p>Couple datasets are formatted for use in a particular Sysplex and cannot be used by a Sysplex other than the one for which they have been formatted.</p>
string Volser	This is the volume serial of the logical volume on which the couple dataset is defined.
string DeviceNumber	<p>This is the z/OS device number of the logical volume on which the couple dataset is defined. The device number is local to the z/OS system from which this instance was obtained.</p> <p>A logical volume may have different device numbers on different z/OS systems in the Sysplex, even though it is the same logical volume being shared by the different z/OS systems.</p>
string NarrativeInfo	This property contains information used by the couple dataset owner to provide additional descriptive information about the couple dataset and its usage. This information includes formatting characteristics and any special functions or attributes that the couple dataset supports.
string Type	This property identifies the type of couple dataset the instance represents. Some examples of couple dataset types include CFRM and SYSPLEX. There are other types of couple datasets, although not all of them are externalized through CIM.
boolean IsPrimary	<p>This property identifies whether the couple dataset represented by an instance is currently in use as the primary couple dataset for its type.</p> <p>A value of True indicates that this instance represents the couple dataset that is currently in use as the primary couple dataset of its type.</p>
boolean IsAlternate	<p>This property identifies whether the couple dataset represented by an instance is currently in use as the alternate couple dataset "for its type.</p> <p>A value of True indicates that this instance represents the couple dataset that is currently in use as the alternate couple dataset of its type.</p>
uint32 MaximumNumberOfSystems	This property identifies the number of z/OS

	systems in the Sysplex that the couple dataset represented by this instance was formatted to support.
datetime FormatTime	<p>This property identifies the local time that the couple dataset was formatted.</p> <p>Note: This property is in the local time of the operating system host servicing the request.</p>
boolean IsSynchronized	<p>This property applies only to instances representing couple datasets that are currently in use as the alternate couple dataset for their type.</p> <p>A value of True indicates that the couple dataset has been fully synchronized with the primary couple dataset of its type.</p> <p>A value of False indicates that the couple dataset is still in the process of synchronizing with the primary couple dataset of its type.</p> <p>An alternate couple dataset must be fully synchronized with the primary couple dataset of its type in order to provide failover capability in the event of an error affecting the primary couple dataset.</p>
boolean ErrorState	This property identifies whether the couple dataset is in an error state. When True, the couple dataset has experienced a permanent error and is in the process of being removed from active use.
uint32 NumberOfStructures	This is the number of coupling facility (CF) structures that the CFRM couple dataset is formatted to support. It is the maximum number of structures that can be defined for use in a policy contained in this couple dataset.
uint32 NumberOfConnectors	Connectors are programs running under z/OS that establish a connection to a CF structure. This property identifies the number of connectors per structure that the couple dataset is formatted to support. It is the maximum number of concurrent connectors that can be supported for each structure defined in the couple dataset.
uint32 NumberOfCFs	This is the number of coupling facilities the couple dataset is formatted to support. It is the maximum number of CFs that can be defined for use in a CFRM policy contained in this couple dataset.
uint32 NumberOfPolicies	This is the number of administrative (inactive) policies that the couple dataset is formatted to support.
Methods	
uint32 SwitchPrimary()	This method switches the couple dataset represented by this instance as follows:

If the instance represents a current in-use alternate couple dataset, it is switched to become the current primary couple dataset. If the alternate couple dataset is not fully synchronized or is in an error state, the method returns an error.

If the instance represents a current in-use primary couple dataset, then it is switched out and the current in-use alternate couple dataset is switched to become the primary. If there is no current in-use alternate couple dataset or the in-use alternate couple dataset is not fully synchronized or in an error state, the method returns an error.

This method functions like the z/OS operator command:

```
SETXCF COUPLE,TYPE=___,PSWITCH
```

IBMzOS_CouplingFacility

Purpose

This class represents a zSeries Coupling Facility, which is the system that manages a Sysplex (System Complex).

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CouplingFacilityProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CouplingFacilityProvider.so

Properties

string Caption	A short description of the class. Returns <i>'IBM z/OS Coupling Facility'</i> .								
string Description	A description of the class. Returns <i>This is an IBM z/OS Coupling Facility</i> .								
string ElementName	Name given to this instance of the class (same as Name)								
datetime InstallDate	A datetime value indicating when the object was installed. A lack of a value does not indicate that the object is not installed.								
string Name	<p>Coupling Facility Logical Name as assigned by CFRM policy definitions.</p> <p>Note: CF Name is not considered an immutable property of a Coupling Facility, since the name can be changed via a CFRM policy update. The physical CF information is the immutable identification information.</p>								
uint16 OperationalStatus []	<p>The current status of the CF (summarized from more granular CF state information):</p> <table><tr><td>0</td><td>Unknown</td></tr><tr><td>2</td><td>OK</td></tr><tr><td>6</td><td>Error</td></tr><tr><td>9</td><td>Stopping</td></tr></table>	0	Unknown	2	OK	6	Error	9	Stopping
0	Unknown								
2	OK								
6	Error								
9	Stopping								
string StatusDescriptions []	Strings describing the various Operational Status values.								
string Status	A string indicating the current status								
uint16 EnabledState	Indicates the Enabled or Disabled state.								
string OtherEnabledState	String describing the Enabled State value								
uint16 RequestedState	The last requested State								
uint16 EnabledDefault	Indicates the default value for Enabled State								
datetime TimeOfLastStateChange	The date and time Enabled State was last changed.								

uint64 IdentityToken [key]	The generated identity value for sysplex cluster. (Part 1 of 2)
string IdentityName [key]	The generated identity value for sysplex cluster. (Part 2 of 2)
string MachineType	Machine type of the server hosting the CF
string Manufacturer	Name of the manufacturer of the server hosting the CF
string ManufacturerPlant	The plant number where the machine was manufactured
string SerialNumber	A manufacturer assigned number to identify the server hosting the CF
uint8 LPARid	Platform-assigned ID of a logical partition in which the CF is running. Null if the Computer System is not virtualized
uint32 CFLevel	Facility operational (functionality) level
uint32 State	CF Operational State (summarized from more granular CF state information): 1 Okay 2 Unknown 6 Error 9 Stopping
uint16 NumberOfProcessors	Total number of CF processors
uint16 CPUUtilization	Percent CF processor utilization
uint32 FreeSpace	Currently unused storage available in the CF (in number of 4KB blocks)
uint32 TotalSpace	Total storage available in the CF (in number of 4KB blocks)
uint32 FreeDumpSpace	Currently unused allocated dump storage available in the CF (in number of 4KB blocks)
uint32 TotalDumpSpace	Total allocated dump storage available in the CF (in number of 4KB blocks)
uint32 StorageIncrementSize	Storage increment. The number of 4K blocks in a single storage increment in this CF.
boolean Standalone	Coupling Facility Standalone indicator: TRUE Not Standalone FALSE Standalone
boolean Volatile	Indicator of whether this CF is volatile or nonvolatile (based on battery backup or standby power source)
boolean CPUType	Indicates whether all of the CF processors are shared, or whether at least one is dedicated: TRUE All shared FALSE Some are dedicated
boolean MaintenanceMode	Indicates whether the CF is currently in Maintenance mode: TRUE Not in Maintenance mode

	FALSE	CF is in Maintenance mode
boolean RecoveryMgrSite	TRUE	Recovery Manager is not active or the CF does not reside at the recovery site
	FALSE	Recover Manager is active and the CF resides at the recovery site.
string SiteName		Name of the SITE specified in the CFRM policy.
string CPCID		Coupling Facility's Central Processor Complex (CPC) ID.
string CFCCReleaseLevel		The release level of the CFCC code.
string CFCCServiceLevel		The service level of the CFCC code.
datetime CFCCCodeBuildDate		The date and time that the CFCC code was built.

Methods

uint32 StartCFMaintenanceMode()

Sets the maintenance mode of the specified coupling facility to ON.

When a CF is in maintenance mode, the CF is not eligible for CF structure allocation purposes and all structure allocation processes will modify their CF selection processing accordingly.

uint32 StopCFMaintenanceMode()

Sets the maintenance mode of the specified coupling facility to OFF.

When a CF is no longer in maintenance mode, the CF is eligible for CF structure allocation purposes.

Associations

IBMzOS_HostedCFStructure

Source	IBMzOS_CFStructure
Target	IBMzOS_CouplingFacility
see	page 229

IBMzOS_UsesCFs

Source	IBMzOS_SysplexNode
Target	IBMzOS_CouplingFacility
see	page 230

Indications

IBMzOS_CouplingFacilityInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_CouplingFacility class has been created.

IBMzOS_CouplingFacilityInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_CouplingFacility class has been deleted.

IBMzOS _CouplingFacilityInstModification

A 'life cycle' indication that indicates that an instance of the IBMzOS_CouplingFacility class has been modified.

IBMzOS_CouplingFunction

Purpose

This class represents an abstraction of z/OS clustering capabilities. The clustering capabilities are referred to as coupling functions, each serving a unique purpose in a z/OS Systems Complex (Sysplex). Coupling functions are capabilities that are facilitated through the use of:

- Couple datasets, which serve as repositories.
- Coupling facilities, which are used by z/OS systems to cache data structures, serialization structures and provide signaling capabilities to z/OS systems participating in a Sysplex.
- Cross-System Coupling Facility (XCF) software, which is a component of z/OS that provides functions to support cooperation between authorized programs running within a Sysplex.

Coupling functions include such capabilities as basic Sysplex support and Coupling Facility Resource Manager (CFRM) support. There are other such coupling functions supported by z/OS, though not all of them may be externalized through CIM providers.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CouplingFunctionProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CouplingFunctionProvider.so

Properties

string Caption	A short description of the class.
string Description	A description of the class.
string ElementName	Name given to this instance of the class.
datetime InstallDate	A datetime value indicating when the object was installed. A lack of a value does not indicate that the object is not installed.
string Name [key]	Name of the coupling function
uint16 OperationalStatus []	The current status of the SysplexCoupleDataset: 0 = Unknown 2 = OK 6 = Error 9 = Stopping
string StatusDescriptions []	Strings describing the various Operational Status values.
string Status	A string indicating the current status
uint16 EnabledState	Indicates the Enabled or Disabled state.
string OtherEnabledState	String describing the Enabled State value.

uint16 RequestedState	The last requested State.
uint16 EnabledDefault	Indicates the default value for Enabled State.
datetime TimeOfLastStateChange	The date and time Enabled State was last changed.
uint32 Redundancy	This identifies the level of couple dataset redundancy currently active for the coupling function. 0 No couple datasets in use. The coupling function is not active. 1 Primary couple dataset in use. 2 Primary and alternate couple dataset are in use.
string ActivePolicyName	Specifies the name of the active policy for the coupling function. Instances of coupling functions such as SYSPLEX, which have no policy, will have a null string value.
datetime TimeActivePolicyStarted	The local date and time that the active policy was started. Note: This property is in the local time of the operating system host servicing the request.
boolean isActive	Identifies whether the coupling function is active. Coupling functions with no primary CDS are considered inactive. Coupling functions that support policies will be identified as active if they have a primary couple dataset in use, even if there is not active policy.

Methods

uint32 StartPolicy()	This method activates (starts) the specified policy. The policy specified by the name parameter must be an administrative policy defined in the primary couple dataset currently in use by the coupling function.
uint32 StopPolicy()	This method inactivates the currently active policy. For Coupling Facilities (CFs) or structures that are actively being used, not all aspects of the policy may become inactive immediately. These changes will become pending until the resources in question are no longer being used by programs operating in the Sysplex.
uint32 DeletePolicy()	This method deletes the specified administrative policy. The policy specified by the name parameter must be an administrative policy defined in the primary couple dataset currently in use by the coupling function.
uint32 SwitchPrimary()	This method makes the current in-use alternate

couple dataset the current primary couple dataset for the type represented by the coupling function instance.

The current in-use primary couple dataset at the time this method is invoked, upon successful completion of the method, will no longer be recognized by XCF and the coupling function instance will be operating solely with a primary couple dataset.

This method is similar to the z/OS operator command:

```
SETXCF COUPLE,TYPE=__,PSWITCH
```

uint32 MakeAlternate()

This method makes the specified couple dataset the current in use alternate couple dataset for the type represented by the coupling function instance.

The type of the specified couple dataset must be compatible with the coupling function instance for which the method was invoked.

The specified couple dataset must be a newly formatted couple dataset, formatted specifically for use in the Sysplex in which the coupling function instance exists. The method will fail if the specified couple dataset is currently or was previously active in the Sysplex.

The specified couple dataset may be one created using the Duplicate method or one created manually via the XCF couple dataset format utility (IXCL1DSU).

uint32 Duplicate()

This method duplicates the characteristics of the currently active primary couple dataset, for the type represented by the coupling function instance, to a new couple dataset. The name of the new couple dataset and the volume serial of the logical volume on which it will be allocated must be specified by the method invoker. The type of the couple dataset is determined by the coupling function instance.

Associations

IBMzOS_UsesCouplingFunctions

Source	IBMzOS_Sysplex
Target	IBMzOS_CouplingFunction
see	page 231

IBMzOS_UsesSysplexCoupleDatasets

Source	IBMzOS_CouplingFunction
Target	IBMzOS_SysplexCoupleDataset
see	page 231

IBMzOS_UsesCFRMCoupleDatasets

Source	IBMzOS_CouplingFunction
Target	IBMzOS_CFRMCoupleDataset
see	page 231

IBMzOS_SFMAAttributes

Purpose

An array of embedded instances of this class is used as input parameter to method SetSFMAAttributes() (see “Methods” on page 222).

Properties

uint64 IdentityToken	Is the 'IdentityToken' of the SysplexNode whose SFM attributes are to be modified. The IdentityToken is a 64 bit unsigned integer that must be converted to a 20 character field, padded on the left with the character zero ('0'). An IdentityToken and IdentityName of '0' indicates that default values should be set for all SysplexNodes.								
string IdentityName	Is the 'IdentityName' of the SysplexNode whose SFM attributes are to be modified. An IdentityToken and IdentityName of '0' indicates that default values should be set for all SysplexNodes.								
boolean SetSystemWeight	Indicates that the SFM_Weight property should be updated.								
boolean SetSystemSFMAAction	Indicates that the SFM_Action (and possibly the SFM_Interval) property should be updated.								
boolean SetMemStallTime	Indicates that the SFM stalled member action for the system should be updated.								
boolean ResetMemStallTime	Indicates that the SFM stalled member action for the system should be cleared.								
uint32 System_Weight	Is the new SFM weight value. The SFM weight is a 32 bit unsigned integer that must be converted to a 10 character field, padded on the left with the character zero ('0').								
uint32 SFM_Action	Is the new SFM action value. Valid character values are: <table><tr><td>1</td><td>Prompt operator</td></tr><tr><td>2</td><td>Isolate</td></tr><tr><td>3</td><td>System reset</td></tr><tr><td>4</td><td>Deactivate</td></tr></table>	1	Prompt operator	2	Isolate	3	System reset	4	Deactivate
1	Prompt operator								
2	Isolate								
3	System reset								
4	Deactivate								
uint32 SFM_Interval	Is the time in seconds corresponding to the SFM action. It is valid only when the action is being set to isolate (2), SystemReset (3), or Deactivate (4). The time is a 32 bit unsigned integer that must be converted to a 10 character field, padded on the left with the character zero ('0').								
uint32 MemStallTime	Is the time in seconds that must pass before SFM takes action against a stalled member causing signal sympathy sickness.								

IBMzOS_Sysplex

Purpose

This class represents a zSeries Sysplex (System Complex).

Inheritance

A subclasses is IBMzOS_SysplexNode (see “IBMzOS_SysplexNode” on page 225).

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SysplexProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SysplexProvider.so

Properties

string Caption	A short description of the class.								
string Description	A description of the class.								
string ElementName	Name given to this instance of the class.								
datetime InstallDate	A datetime value indicating when the object was installed. A lack of a value does not indicate that the object is not installed.								
string Name	Sysplex name								
uint16 OperationalStatus []	The current status of the Sysplex, based on the states of the systems it is comprised of: <table><tr><td>0</td><td>Unknown</td></tr><tr><td>2</td><td>OK</td></tr><tr><td>6</td><td>Error</td></tr><tr><td>9</td><td>Stopping</td></tr></table>	0	Unknown	2	OK	6	Error	9	Stopping
0	Unknown								
2	OK								
6	Error								
9	Stopping								
string StatusDescriptions []	Strings describing the various Operational Status values.								
string Status	A string indicating the current status								
uint16 EnabledState	Indicates the Enabled or Disabled state.								
string OtherEnabledState	String describing the Enabled State value								
uint16 RequestedState	The last requested State								
uint16 EnabledDefault	Indicates the default value for Enabled State								
datetime TimeOfLastStateChange	The date and time Enabled State was last changed.								
uint64 IdentityToken [key]	The generated identity value for sysplex cluster. (Part 1 of 2)								
string IdentityName [key]	The generated identity value for sysplex cluster. (Part 2 of 2)								
uint32 Type	The type of sysplex cluster: <table><tr><td>1</td><td>Local</td></tr></table>	1	Local						
1	Local								

	2	Monoplex
	3	Multisystem

uint32 State State of the Sysplex, based on the states of the systems it is comprised of:

1	Okay
2	Unknown
3	Error
4	Stopping

z/OS, will only report a state of 'Okay' (1)

boolean SysplexConnectionFail Corresponds to the CONNFAIL attribute in the SFM policy. Indicates whether or not action taken when connectivity failure occurs in the sysplex.

Methods

uint32 SetSFMAAttributes() Updates the SFM policy to set the SFM weights for each system specified in the input, SystemArray, and will set the Sysplex Connect Fail property value for the sysplex.

Successful execution of this method will indicate that all the entries in the SystemArray were processed. If any of the system entries could not be processed the method will return an error.

An array of embedded instances of class IBMzOS_SFMAAttributes is used as input parameter to this method (see "IBMzOS_SFMAAttributes" on page 220).

uint32 SetSysplexConnFail() Sets the ConnectionFail property value.

uint32 ResetSysplexConnFail() Resets the ConnectionFail property value.

uint32 StartReallocate() Analyzes all structures in the Sysplex and performs corrective actions on structures that are operating outside current CFRM policy parameters.

Sysplex Process Completion Indication will be generated when asynchronous processing has completed.

uint32 StopReallocate() Stops the reallocation of CF structures.

Sysplex Process Completion Indication will be generated when asynchronous processing has completed.

uint32 ForceReallocate() Forces an in process reallocation to be stopped.

Sysplex Process Completion Indication will be generated when asynchronous processing has completed.

Associations

IBMzOS_CollectionOfCFs	
Source	IBMzOS_Sysplex
Target	IBMzOS_CouplingFacility

see page 228

IBMzOS_CollectionOfSysplexNodes

Source IBMzOS_Sysplex

Target IBMzOS_SysplexNode

see page 229

IBMzOS_UsesCouplingFunctions

Source IBMzOS_Sysplex

Target IBMzOS_CouplingFunction

see page 231

Indications

IBMzOS_SysplexInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_Sysplex class has been created. The Sysplex supports services that may report on cluster manageable resources. This event occurs when each system has IPLed into the Sysplex with a Cluster capable Sysplex Couple Dataset. This event occurs on each system when a Cluster capable dataset has been brought into use.

IBMzOS_SysplexInstModification

A 'life cycle' indication that indicates that an instance of the IBMzOS_Sysplex class has been modified. The SysplexConnectionFail property has changed.

IBMzOS_Sysplex_CFRM_CDS_Initialized

A 'process' indication that indicates that the process of reallocating the CF Structures has completed. CFRM Resources (Coupling Facility, CF Structure and CF Structure Connectors) has been defined to the Sysplex. The z/OS Cluster MR Services should be issued to obtain the CFRM resource instances in use by the Sysplex.

IBMzOS_Sysplex_ReallocateInitiated

A 'process' indication that indicates that the Start Reallocate CF Structures process has been initiated. The reallocate command may have been initiated by an operator command or through a CIM StartReallocate() method.

IBMzOS_Sysplex_ReallocateCompleted

A 'process' indication that indicates that the Start, Stop, or Force Reallocate CF Structures command has completed processing. The reallocate command may have been initiated by an operator command or through a CIM StartReallocate(), StopReallocate(), or ForceReallocate() methods.

IBMzOS_SysplexCoupleDataset

Purpose

This class represents the z/OS Systems Complex (Sysplex) couple datasets. A Sysplex couple dataset contains Sysplex-wide data about systems, groups, and members that use Cross-System Coupling Facility (XCF) services. All z/OS systems in a Sysplex must have connectivity to the Sysplex couple dataset.

A Sysplex couple dataset can be the primary, or optionally, the active alternate couple dataset supporting the Sysplex coupling function. Minimally, a Sysplex couple dataset must be in use as the active primary Sysplex couple dataset for the Sysplex function to be active.

Inheritance

IBMzOS_CoupleDataset
← IBMzOS_SysplexCoupleDataset

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SysplexCoupleDatasetProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SysplexCoupleDatasetProvider.so

Properties

string Name	The name of the couple dataset represented by an instance of this class.
uint32 NumberOfGroups	The number of XCF groups that the couple dataset is formatted to support. It is the maximum number of concurrently active XCF groups that can be active in the Sysplex while this couple dataset is in use as the primary Sysplex couple dataset.
uint32 NumberOfMembers	The number of XCF members per group that this couple dataset is formatted to support. Each XCF group in the Sysplex may have up to this number of concurrently active programs (XCF members) participating in the group.
uint32 GRSLevel	Indicates whether or not this couple dataset supports the use of Global Resource Serialization (GRS) STAR for Sysplex-scope resource serialization. GRS STAR provides improved performance and reliability over the use of GRS RING.

IBMzOS_SysplexNode

Purpose

This class represents a node in a zSeries Sysplex (System Complex). There is one node in a Sysplex for every z/OS system that comprises the Sysplex.

Inheritance

IBMzOS_Sysplex
← IBMzOS_SysplexNode

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SysplexNodeProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SysplexNodeProvider.so

Properties

string Caption	A short description of the class.
string Description	A description of the class.
string ElementName	Name given to this instance of the class.
datetime InstallDate	A datetime value indicating when the object was installed. A lack of a value does not indicate that the object is not installed.
string Name	SysplexNode name which is the same as the Operating System's System Name
uint16 OperationalStatus []	The current status of the SysplexNode: 0 Unknown 2 OK 6 Error 9 Stopping
string StatusDescriptions []	Strings describing the various Operational Status values.
string Status	A string indicating the current status
uint16 EnabledState	Indicates the Enabled or Disabled state.
string OtherEnabledState	String describing the Enabled State value
uint16 RequestedState	The last requested State
uint16 EnabledDefault	Indicates the default value for Enabled State
datetime TimeOfLastStateChange	The date and time Enabled State was last changed.
uint64 IdentityToken [key]	The generated identity value for sysplex cluster. (Part 1 of 2)
string IdentityName [key]	The generated identity value for sysplex cluster. (Part 2 of 2)

uint32 State	State of node: 1 Okay 2 Unknown 3 Error 4 Stopping
uint32 SubState	SubState of node: 1 Normal 2 StatusUpdateMissing 3 InActive 4 IPLing Valid when State = Error. Not valid for all other system states.
uint32 SystemSFMWeight	Corresponds to System Weight attribute on SFM policy. Relative system weight used by clique algorithm following Sysplex connectivity failure
uint32 SystemFDIInterval	Corresponds to Failure Detection Interval attribute of SFM policy. Time interval during which missing status updates are tolerated. When failure interval is exceeded the SystemPartitionPolicy determines response
uint32 SystemSFMAction	Corresponds to Action attribute on SFM policy. One of four actions are settable in the SFM policy: 1 Prompt Operator 2 Isolate (isolate system using the CF fencing controls) 3 System Reset Partition 4 Deactivate Partition (deactivate the partition using the HMC controls)
uint32 SystemSFMInterval	When the System SFM Action is Automatic, System Reset, or Deactivate, this property will contain the time value in seconds corresponding to the SFM action.
uint32 SystemMemStallTime	For MEMSTALLTIME(stalltime), SFM will take action to resolve a sympathy sickness problem attributed to a stalled XCF group member if the problem persists for stalltime seconds.
uint32 SystemOpNotify	The length of time after a system is status update missing before SFM takes action. For PROMPT, the interval used is the XCF OPNOTIFY value.

Methods

uint32 SetSystemFDIInterval()	Sets the SFM failure detection interval (FDI) for the system.
--------------------------------------	---

Associations

IBMzOS_HostedCFStrConnector	
Source	IBMzOS_SysplexNode
Target	IBMzOS_CFStructureConnector
see	page 230
IBMzOS_UsesCFs	

Source	IBMzOS_SysplexNode
Target	IBMzOS_CouplingFacility
see	page 230

Indications

IBMzOS_SysplexNodeInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_SysplexNode class has been created.

IBMzOS_SysplexNodeInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_SysplexNode class has been deleted.

IBMzOS_SysplexNodeInstModification

A 'life cycle' indication that indicates that an instance of the IBMzOS_SysplexNode class has been modified.

Association IBMzOS_CFStrDependsOn

Purpose

This class associates an IBMzOS_CFStructure with an IBMzOS_CFStructureConnector.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CFStrDependsOnProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CFStrDependsOnProvider.so

Indications

IBMzOS_CFStrDependsOnInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStrDependsOn association class has been created.

IBMzOS_CFStrDependsOnInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_CFStrDependsOn association class has been deleted.

Association IBMzOS_CollectionOfCFs

Purpose

This class associates an IBMzOS_Sysplex with an IBMzOS_CouplingFacility.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CollectionOfCFsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CollectionOfCFsProvider.so

Indications

IBMzOS_CollectionOfCFsInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_CollectionOfCFs association class has been created.

IBMzOS_CollectionOfCFsInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_CollectionOfCFs association class has been deleted.

Association IBMzOS_CollectionOfSysplexNodes

Purpose

This class associates an IBMzOS_Sysplex with an IBMzOS_SysplexNode.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CollectionOfSysplexNodesProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CollectionOfSysplexNodesProvider.so

Indications

IBMzOS_CollectionOfSysplexNodesInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_CollectionOfSysplexNodes association class has been created.

IBMzOS_CollectionOfSysplexNodesInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_CollectionOfSysplexNodes association class has been deleted.

Association IBMzOS_HostedCFStructure

Purpose

This class associates an IBMzOS_CFStructure with an IBMzOS_CouplingFacility.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_HostedCFStructureProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_HostedCFStructureProvider.so

Indications

IBMzOS_HostedCFStructureInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_HostedCFStructure association class has been created.

IBMzOS_HostedCFStructureInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_HostedCFStructure association class has been deleted.

Association IBMzOS_HostedCFStrConnector

Purpose

This class associates an IBMzOS_SysplexNode with an IBMzOS_CFStructureConnector.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_HostedCFStrConnectorProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_HostedCFStrConnectorProvider.so

Indications

IBMzOS_HostedCFStrConnectorInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_HostedCFStrConnector association class has been created.

IBMzOS_HostedCFStrConnectorInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_HostedCFStrConnector association class has been deleted.

Association IBMzOS_UsesCFs

Purpose

This class associates an IBMzOS_SysplexNode with an IBMzOS_CouplingFacility.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_UsesCFsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_UsesCFsProvider.so

Indications

IBMzOS_UsesCFsInstCreation

A 'life cycle' indication that indicates that an instance of the IBMzOS_UsesCFs association class has been created.

IBMzOS_UsesCFsInstDeletion

A 'life cycle' indication that indicates that an instance of the IBMzOS_UsesCFs association class has been deleted.

Association IBMzOS_UsesCFRMCoupleDatasets

Purpose

This class associates an instance of IBMzOS_CouplingFunction with instances of IBMzOS_CFRMCoupleDataset classes.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_UsesCFRMCoupleDatasetsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_UsesCFRMCoupleDatasetsProvider.so

Association IBMzOS_UsesCFRMPolicies

Purpose

This class associates an instance of the IBMzOS_CFRMCoupleDataset class with instances of the IBMzOS_CFRMPolicy classes.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_UsesCFRMPoliciesProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_UsesCFRMPoliciesProvider.so

Association IBMzOS_UsesCouplingFunctions

Purpose

This class associates an instance of the IBMzOS_Sysplex class with instances of the IBMzOS_CouplingFunction classes.

Association IBMzOS_UsesSysplexCoupleDatasets

Purpose

This class associates an instance of the IBMzOS_CouplingFunction class with instances of the IBMzOS_SysplexCoupleDataset classes.

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_UsesSysplexCoupleDatasetsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

`libcmpiIBMzOS_UsesSysplexCoupleDatasetsProvider.so`

Storage management classes

CIM_FCPort

Purpose

This class represents capabilities and management of a Fiber Channel Port device.

Inheritance

The z/OS specific subclass is IBMzOS_FCPort (see IBMzOS_FCPort on page 236).

CIM_FCPortStatistics

Inheritance

The z/OS specific subclass is IBMzOS_FCPortStatistics (see “IBMzOS_FCPortStatistics” on page 239).

CIM_PortController

Inheritance

The z/OS specific subclass is IBMzOS_PortController (see “IBMzOS_PortController” on page 241).

CIM_Product

Inheritance

The z/OS specific subclass is IBMzOS_Product (see “IBMzOS_Product” on page 243).

CIM_ProtocolEndpoint

Inheritance

The z/OS specific subclass is IBMzOS_SBProtocolEndpoint (see “IBMzOS_SBProtocolEndpoint” on page 244).

CIM_SoftwareIdentity

Inheritance

The z/OS specific subclass is IBMzOS_SoftwareIdentity (see “IBMzOS_SoftwareIdentity” on page 246).

CIM_StorageExtent

Inheritance

CIM_StorageExtent is supported as a superclass of IBMzOS_LogicalDisk (see “IBMzOS_LogicalDisk” on page 148) and won't have a separate implementation.

CIM_ManagedElement

← CIM_ManagedSystemElement

← CIM_LogicalElement

← CIM_EnabledLogicalElement

← CIM_LogicalDevice

← CIM_StorageExtent

Used by the following CIM profiles

- Host Discovered Resources Profile

Association CIM_ControlledBy

Purpose

The CIM_ControlledBy relationship indicates which devices such as IBMzOS_FCPort are controlled by a CIM_Controller such as IBMzOS_PortController on z/OS.

Inheritance

The z/OS specific subclass is IBMzOS_ControlledBy (see “Association IBMzOS_ControlledBy” on page 249).

Association CIM_DeviceSAPImplementation

Inheritance

The z/OS specific subclass is IBMzOS_SBDeviceSAPImplementation (see “Association IBMzOS_SBDeviceSAPImplementation” on page 256).

Association CIM_ElementSoftwareIdentity

Inheritance

The z/OS specific subclass is IBMzOS_ElementSoftwareIdentity (see “Association IBMzOS_ElementSoftwareIdentity” on page 252).

Association CIM_ElementStatisticalData

Inheritance

The z/OS specific subclass is IBMzOS_FCPortStatisticalData (see “Association IBMzOS_FCPortStatisticalData” on page 253).

Association CIM_HostedAccessPoint

Inheritance

The z/OS specific subclass is IBMzOS_SBHostedAccessPoint (see “Association IBMzOS_SBHostedAccessPoint” on page 257).

Association CIM_InitiatorTargetLogicalUnitPath

Inheritance

The z/OS specific subclass is IBMzOS_SBInitiatorTargetLogicalUnitPath (see “Association IBMzOS_SBInitiatorTargetLogicalUnitPath” on page 258).

Association CIM_InstalledSoftwareIdentity

Inheritance

The z/OS specific subclass is IBMzOS_InstalledSoftwareIdentity (see “Association IBMzOS_InstalledSoftwareIdentity” on page 254).

Association CIM_ProductElementComponent

Inheritance

The z/OS specific subclass is IBMzOS_ProductElementComponent (see “Association IBMzOS_ProductElementComponent” on page 255).

Association CIM_SystemDevice

Inheritance

The z/OS specific subclasses are

- IBMzOS_CSFCPort (see “Association IBMzOS_CSFCPort” on page 250) and
- IBMzOS_CSFCPortController (see “Association IBMzOS_CSFCPortController” on page 251).

IBMzOS_FCPort

Purpose

The IBMzOS_FCPort class defines the capabilities and management of a Fiber Channel Port device on z/OS.

Inheritance

```
CIM_ManagedElement
  ← CIM_ManagedSystemElement
  ← CIM_LogicalElement
  ← CIM_EnabledLogicalElement
  ← CIM_LogicalDevice
  ← CIM_LogicalPort
  ← CIM_NetworkPort
  ← CIM_FCPort
  ← IBMzOS_FCPort
```

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

```
IBMzOS_FCPortProviderModule
```

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

```
libcmpiIBMzOS_FCPortProvider.so
```

Used by the following CIM profiles

- Storage HBA profile

Properties

string Caption	Returns IBM z/OS FCPort.
string Description	Returns This is a z/OS FCPort.
string ElementName	Returns <i>LPARName:CSSID:CHPID</i> , where <i>LPARName</i> is the name of the logical partition - empty if z/OS does not run in an LPAR <i>CSSID</i> is the channel subsystem ID <i>CHPID</i> is the channel path ID
string Name	Returns <i>LPARName:CSSID:CHPID</i> , where <i>LPARName</i> is the name of the logical partition - empty if z/OS does not run in an LPAR <i>CSSID</i> is the channel subsystem ID <i>CHPID</i> is the channel path ID
uint16 OperationalStatus []	Returns the current status of the FCPort: 2 OK

	11	Stopped
uint16 EnabledState	Returns	
	2	enabled
uint16 RequestedState	Returns	
	2	enabled
uint16 EnabledDefault	Indicates the administrator's default or startup configuration for the enabled state of an element.	
	Always returns	
	2	enabled
string SystemCreationClassName	Indicates the system's CreationClassName.	
	Returns IBMzOS_ComputerSystem.	
string SystemName	Displays the fully qualified host name of the system.	
string CreationClassName	Indicates the name of the class or the subclass used in the creation of an instance.	
	Returns IBMzOS_FCPort.	
string DeviceID	Displays a unique address or other identifying name for the LogicalDevice.	
	Returns	
	<i>WWPN:LPARID</i>	
	or	
	<i>NodeDescriptor:LPARID</i>	
	when the WWPN cannot be retrieved.	
	where	
	<i>WWPN</i> is the World Wide Port Number	
	<i>LPARID</i> is the logical partition ID	
	<i>NodeDescriptor</i>	
	is the node descriptor	
uint16 PortNumber	Returns the logical port number (CHPID).	
uint64 Speed	Returns the bandwidth of the port in bits per second - 0 if z/OS does not run in an LPAR	
uint64 MaxSpeed	Returns the maximum bandwidth of the port in bits per second - 0 if z/OS does not run in an LPAR	
uint16 UsageRestriction	Returns	
	4	not restricted
uint16 PortType	Specifies the specific mode currently enabled for the port.	
	Returns	
	10	N-Port
uint16 LinkTechnology	Specifies the type of link.	
	Returns	

	4	FC
string PermanentAddress	Defines the network address of the port.	
	Returns	
	<i>WWPN</i>	if a network address is available
	NULL	else
uint64 SupportedMaximumTransmissionUnit	Specifies the maximum transmission unit (MTU) that can be supported.	
	Returns 8192.	
uint64 ActiveMaximumTransmissionUnit	Specifies the active or negotiated maximum transmission unit (MTU) that can be supported.	
	Returns 8192.	
uint16 SupportedCOS []	Indicates the Fibre Channel Class of Service that is supported.	
	Returns 3.	
uint16 ActiveCOS []	Indicates the Fibre Channel Class of Service that is active. Returns 3.	
uint16 SupportedFC4Types []	Indicates the supported Fibre Channel FC-4 protocol.	
	Returns	
	27	FC-SB-x channel
uint16 ActiveFC4Types []	Indicates the currently running Fibre Channel FC-4 protocol.	
	Returns	
	27	FC-SB-x channel

Associations

IBMzOS_FCPortStatisticalData	
ManagedElement	IBMzOS_FCPort
Stats	IBMzOS_FCPortStatistics
see	page 253
IBMzOS_ControlledBy	
Source	IBMzOS_PortController
Target	IBMzOS_FCPort
see	page 249
IBMzOS_SBDeviceSAPImplementation	
Source	IBMzOS_FCPort
Target	IBMzOS_SBProtocolEndpoint
see	page 256
IBMzOS_CSFCPort	
Source	IBMzOS_ComputerSystem
Target	IBMzOS_FCPort
see	page 250

IBMzOS_FCPortStatistics

Purpose

The IBMzOS_FCPort class defines the statistics for the FCPort on z/OS.

Inheritance

CIM_ManagedElement
← CIM_StatisticalData
← CIM_NetworkPortStatistics
← CIM_FCPortStatistics
← IBMzOS_FCPortStatistics

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_FCPortStatisticsProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_FCPortStatisticsProvider.so

Used by the following CIM profiles

- Storage HBA profile

Properties

string Caption	Returns IBM z/OS FCPortStatistics.
string Description	Returns This is a z/OS FCPortStatistics.
string InstanceID	Returns IBM:FCPortStat:WWPN:LPARID or IBM:FCPortStat:NodeDescriptor:LPARID when the WWPN cannot be retrieved.
string ElementName	Returns FCPortStat:LPARName:CSSID:CHPID, where <i>LPARName</i> is the name of the logical partition - empty if z/OS does not run in an LPAR <i>CSSID</i> is the channel subsystem ID <i>CHPID</i> is the channel path ID
uint64 BytesTransmitted	Returns the total number of bytes that are transmitted, including framing characters - 0 if z/OS does not run in an LPAR
uint64 BytesReceived	Returns the total number of bytes that are received, including framing characters - 0 if z/OS does not run in an LPAR
uint64 PacketsTransmitted	Returns the total number of packets that are transmitted - 0 if z/OS does not run in an LPAR

uint64 PacketsReceived Returns the total number of packets that are received - 0 if z/OS does not run in an LPAR

Associations

IBMzOS_FCPortStatisticalData	
ManagedElement	IBMzOS_FCPort
Stats	IBMzOS_FCPortStatistics
see	page 253

IBMzOS_PortController

Purpose

The IBMzOS_PortController class represents a logical device corresponding to a hardware network port controller on z/OS. Port controllers provide various features depending on their types and versions. Since it is not possible from inband z/OS instrumentation to distinguish between Ports and PortControllers, the PortController provider returns one instance for each FCPort, using the same key information.

Inheritance

CIM_ManagedElement
← CIM_ManagedSystemElement
← CIM_LogicalElement
← CIM_EnabledLogicalElement
← CIM_LogicalDevice
← CIM_Controller
← CIM_PortController
← IBMzOS_PortController

Module name

The module names of the CMPI providers that are registered for a CIM class which are used by the cimprovider command line tool for the administration of CMPI providers are

IBMzOS_PortControllerProviderModule
IBMzOS_PortControllerIndicationProviderModule

Provider library

The physical names of a CMPI provider's shared object library stored in the hierarchical file system are

libcmpiIBMzOS_PortControllerProvider.so
libcmpiIBMzOS_PortControllerIndicationProvider.so

Used by the following CIM profiles

- Storage HBA profile

Properties

string Caption	Returns IBM z/OS PortController.
string Description	Returns This is a z/OS PortController.
uint16 OperationalStatus []	Returns 2 OK
uint16 EnabledState	Returns 2 enabled
uint16 RequestedState	Returns 2 enabled
uint16 EnabledDefault	Indicates the administrator's default or startup configuration for the enabled state of an element. Returns 2 enabled

string SystemCreationClassName	Returns IBMzOS_ComputerSystem.
string SystemName	Displays the fully qualified host name of the system.
string CreationClassName	Returns IBMzOS_PortController.
string DeviceID	Returns a unique name for the logical device: <i>WWPN : LPARID</i> when the WWPN can be retrieved <i>NodeDescriptor : LPARID</i> else where <i>WWPN</i> is the World Wide Port Number <i>LPARID</i> is the logical partition ID <i>NodeDescriptor</i> is the node descriptor
uint16 ControllerType	Returns 4 FC

Associations

IBMzOS_ControlledBy	
Source	IBMzOS_PortController
Target	IBMzOS_FCPort
see	page 249
IBMzOS_ElementSoftwareIdentity	
Source	IBMzOS_SoftwareIdentity
Target	IBMzOS_PortController
see	page 252

Indications

CIM_InstCreation	A life cycle indication that indicates that an instance of the IBMzOS_PortController class has been created. CIM_IndicationFilter query string: "SELECT * FROM CIM_InstCreation WHERE SourceInstance ISA CIM_PortController"
CIM_InstDeletion	A life cycle indication that indicates that an instance of the IBMzOS_PortController class has been deleted. CIM_IndicationFilter query string: "SELECT * FROM CIM_InstDeletion WHERE SourceInstance ISA CIM_PortController"

For more information on how to subscribe to an indication, see “CIM subscription mechanism” on page 289. Specify your queries using the CIM_IndicationFilter query string (see also “CIM_IndicationFilter” on page 290).

IBMzOS_Product

Purpose

The IBMzOS_Product is a concrete class that aggregates PhysicalElements, software (SoftwareIdentity and SoftwareFeatures), services or other products on z/OS.

For z/OS 1.12, an instance of IBMzOS_Product is created for each FCPort returned by the IBMzOS_FCPort provider.

Inheritance

CIM_ManagedElement

← CIM_Product

← IBMzOS_Product

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_ProductProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_ProductProvider.so

Used by the following CIM profiles

- Storage HBA profile

Properties

string Caption	Returns IBM z/OS Product.
string Description	Returns Represents a z/OS FCPortController Product.
string Name	Returns the DeviceID from IBMzOS_FCPort.
string ElementName	Returns the DeviceID from IBMzOS_FCPort.
string IdentifyingNumber	Returns the DeviceID from IBMzOS_FCPort.
string Vendor	Returns IBM.
string Version	Returns unknown.

IBMzOS_SBProtocolEndpoint

Purpose

The IBMzOS_SBProtocolEndpoint class is used to represent two different entities, Initiator and Target. The Initiator entity describes the protocol endpoint on the computer system side, the target entity describes the protocol endpoint on the disk controller side of a logical disk attached to a computer system.

Protocol endpoints are identified via World Wide Port Numbers (WWPN), which are used as the primary key for the instances of the class IBMzOS_SBProtocolEndpoint, reflected in the name property. For the retrieval of WWPN the IOS services IOSCDR and IOSCHPD have been extended for z/OS 1.13 to facilitate the retrieval of WWPN for the Initiator (IOSCHPD) and Target (IOSCDR) protocol endpoints. Therefore, the retrieval of WWPN through IOSCDR is only possible under the following conditions:

1. The used hardware is at least an IBM System z10™.
2. The requestor or CIM client has UPDATE access to the IOSCDR profile.

Inheritance

CIM_ManagedElement
↳ CIM_ManagedSystemElement
↳ CIM_LogicalElement
↳ CIM_EnabledLogicalElement
↳ CIM_ServiceAccessPoint
↳ CIM_ProtocolEndpoint
↳ IBMzOS_SBProtocolEndpoint

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SBProtocolEndpointProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SBProtocolEndpointProvider.so

Used by the following CIM profiles

- Host Discovered Resources Profile
- Storage HBA profile

Properties

string Caption	Returns IBM z/OS SBProtocolEndpoint.
string Description	Returns This is a z/OS SBProtocolEndpoint.
string Name	The <i>Initiator</i> returns the WWPN of the computer system side. The <i>Target</i> returns the WWPN of the storage controller side.
uint16 OperationalStatus []	Returns 2 OK

uint16 EnabledState	Returns 2 Enabled
uint16 RequestedState	Returns 2 Enabled
uint16 EnabledDefault	Returns 2 Enabled
string SystemCreationClassName	Returns IBMzOS_ComputerSystem
string SystemName	Displays the name of the host system.
string CreationClassName	Returns IBMzOS_SBProtocolEndpoint
uint16 ProtocolIFType	Returns 56 Fibre Channel
string OtherTypeDescription	Returns SB.
uint16 ConnectionType	Returns 2 Fibre Channel
uint16 Role	Returns 2 Initiator or 3 Target

Associations

IBMzOS_SBHostedAccessPoint

Source	IBMzOS_ComputerSystem
Target	IBMzOS_SBProtocolEndpoint (Initiator Instance)
see	page 257

IBMzOS_SBDeviceSAPImplementation

Source	IBMzOS_FCPort
Target	IBMzOS_SBProtocolEndpoint
see	page 256

IBMzOS_SBInitiatorTargetLogicalUnitPath

Initiator	IBMzOS_SBProtocolEndpoint (Initiator Instance)
Target	IBMzOS_SBProtocolEndpoint (Target instance)
LogicalUnit	IBMzOS_LogicalDisk
see	page 258

IBMzOS_SoftwareIdentity

Purpose

The IBMzOS_SoftwareIdentity class provides descriptive information about a software component for asset tracking or installation dependency management.

The idea behind SoftwareIdentity as defined in the SMI-S Storage HBA profile does not match the concepts of z/OS. Therefore this class has only been implemented for formal compliance with the SMI-S Storage HBA profile.

For z/OS 1.12, therefore only one instance of IBMzOS_SoftwareIdentity is created and associated to all PortControllers. .

Inheritance

```
CIM_ManagedElement
  ← CIM_ManagedSystemElement
  ← CIM_LogicalElement
  ← CIM_SoftwareIdentity
  ← IBMzOS_SoftwareIdentity
```

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

```
IBMzOS_SoftwareIdentityProviderModule
```

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

```
libcmpiIBMzOS_SoftwareIdentityProvider.so
```

Used by the following CIM profiles

- Storage HBA profile

Properties

string Caption	Returns IBM z/OS SoftwareIdentity.
string Description	Returns The Software driving the IBMzOS_PortController.
uint16 OperationalStatus []	Returns 2 OK
string InstanceID	Uniquely identifies an instance of this class. Returns IBMzOS:CSSID:LPARID, where CSSID is the channel subsystem ID LPARID is the logical partition ID
string ElementName	Returns IBMzOS:CSSID:LPARID, where CSSID is the channel subsystem ID LPARID is the logical partition ID
string VersionString	Returns the z/OS Version and Release number in the form <i>Major.Minor.Revision</i> , where <i>Major</i> is the z/OS version <i>Minor</i> is the release

	<i>Revision</i>	is the revision number
string Manufacturer		Returns IBM.
uint16 Classifications []		Returns
	2	Driver
		and
	8	Operating System
string TargetOperatingSystems []		Returns z/OS.

Associations

IBMzOS_ElementSoftwareIdentity

Source	IBMzOS_SoftwareIdentity
Target	IBMzOS_PortController
see	page 252

IBMzOS_InstalledSoftwareIdentity

Source	IBMzOS_ComputerSystem
Target	IBMzOS_SoftwareIdentity
see	page 254

Association IBMzOS_ControlledBy

Inheritance

CIM_Dependency
← CIM_DeviceConnection
← CIM_ControlledBy
← IBMzOS_ControlledBy

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_ControlledByProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_ControlledByProvider.so

Used by the following CIM profiles

- Storage HBA profile

Properties

Ref Antecedent	References an IBMzOS_PortController
Ref Dependent	References an IBMzOS_FCPort
Uint16 AccessState	Returns 1 Active
String DeviceNumber	Returns the device number of the IBMzOS_FCPort.
Uint16 AccessMode	Returns 2 ReadWrite

Association IBMzOS_CSFCPort

Inheritance

CIM_Component
← CIM_SystemComponent
← CIM_SystemDevice
← IBMzOS_CSFCPort

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CSFCPortProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CSFCPortProvider.so

Properties

Ref GroupComponent	References an IBMzOS_ComputerSystem
Ref PartComponent	References an IBMzOS_FCPort

Association IBMzOS_CSFCPortController

Inheritance

CIM_Component
← CIM_SystemDevice
← IBMzOS_CSFCPortController

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_CSFCPortControllerProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_CSFCPortControllerProvider.so

Properties

Ref GroupComponent References an IBMzOS_ComputerSystem

Ref PartComponent References an IBMzOS_PortController

Association IBMzOS_ElementSoftwareIdentity

Purpose

The IBMzOS_ElementSoftwareIdentity class allows a Managed Element such as an IBMzOS_PortController to report its software related asset information (such as firmware, drivers, or configuration software) on z/OS.

Inheritance

- CIM_Dependency
- ← CIM_ElementSoftwareIdentity
- ← IBMzOS_ElementSoftwareIdentity

Used by the following CIM profiles

- Storage HBA profile

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_ElementSoftwareIdentityProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_ElementSoftwareIdentityProvider.so

Properties

Ref Antecedent	References an IBMzOS_SoftwareIdentity
Ref Dependent	References an IBMzOS_PortController

Association IBMzOS_FCPortStatisticalData

Purpose

This class associates an IBMzOS_FCPort with IBMzOS_FCPortStatistics.

Inheritance

CIM_ElementStatisticalData

← IBMzOS_FCPortStatisticalData

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_FCPortStatisticalDataProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_FCPortStatisticalDataProvider.so

Properties

Ref ManagedElement

References an IBMzOS_FCPort

Ref Stats

References IBMzOS_FCPortStatistics

Association IBMzOS_InstalledSoftwareIdentity

Purpose

The IBMzOS_InstalledSoftwareIdentity association identifies the Software installed on a system. On z/OS this class has only been implemented for formal compliance with the SMI-S Storage HBA profile and is of limited use.

Inheritance

CIM_InstalledSoftwareIdentity
← IBMzOS_InstalledSoftwareIdentity

Used by the following CIM profiles

- Storage HBA profile

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_InstalledSoftwareIdentityProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_InstalledSoftwareIdentityProvider.so

Properties

Ref System	References an IBMzOS_ComputerSystem
Ref InstalledSoftware	References an IBMzOS_SoftwareIdentity

Association IBMzOS_ProductElementComponent

Inheritance

CIM_Component
← CIM_ProductElementComponent
← IBMzOS_ProductElementComponent

Used by the following CIM profiles

- Storage HBA profile

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_ProductElementComponentProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_ProductElementComponentProvider.so

Properties

Ref GroupComponent

References an IBMzOS_Product

Ref PartComponent

References an IBMzOS_PortController

Association IBMzOS_SBDeviceSAPImplementation

Purpose

The IBMzOS_SBDeviceSAPImplementation class describes an association between a ServiceAccessPoint (SAP) and how it is implemented.

Inheritance

CIM_Dependency
← CIM_DeviceSAPImplementation
← IBMzOS_SBDeviceSAPImplementation

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SBDeviceSAPImplementationProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SBDeviceSAPImplementationProvider.so

Used by the following CIM profiles

- Storage HBA profile

Properties

Ref Antecedent	References an IBMzOS_FCPort
Ref Dependent	References an IBMzOS_SBProtocolEndpoint

Association IBMzOS_SBHostedAccessPoint

Purpose

The IBMzOS_SBHostedAccessPoint class is an association between a Service Access Point and the System on which it is provided.

Inheritance

CIM_Dependency
← CIM_HostedDependency
← CIM_HostedAccessPoint
← IBMzOS_SBHostedAccessPoint

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SBHostedAccessPointProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SBHostedAccessPointProvider.so

Used by the following CIM profiles

- Host Discovered Resources Profile
- Storage HBA profile

Properties

Ref Antecedent	References an IBMzOS_ComputerSystem
Ref Dependent	References an IBMzOS_SBProtocolEndpoint (Initiator instance)

Association IBMzOS_SBInitiatorTargetLogicalUnitPath

Purpose

The IBMzOS_SBInitiatorTargetLogicalUnitPath class is a three way association between an z/OS disk device, identified by the LogicalUnit reference, the channel, identified by the Initiator reference and the control unit, identified by the Target reference. Each permutation of initiator and target ProtocolEndpoints and logical units is considered as a separate path.

Retrieving the data for IBMzOS_SBInitiatorTargetLogicalUnitPath is only possible under the following conditions:

1. The used hardware is at least an IBM System z10.
2. The requestor or CIM client user ID has UPDATE access to the IOSCDR profile.

Inheritance

CIM_InitiatorTargetLogicalUnitPath
← IBMzOS_SBInitiatorTargetLogicalUnitPath

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_SBInitiatorTargetLogicalUnitPathProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libcmpiIBMzOS_SBInitiatorTargetLogicalUnitPathProvider.so

Used by the following CIM profiles

- Host Discovered Resources Profile
- Storage HBA profile

Properties

Ref Initiator References an IBMzOS_SBProtocolEndpoint (Initiator instance)

Ref Target References an IBMzOS_SBProtocolEndpoint (Target instance)

Ref LogicalUnit
References an IBMzOS_LogicalDisk

uint32 State Returns the state of the path:

2	active
4	disabled
8	removed (boxed)
9	transitioning

Indications

CIM_InstCreation
A life cycle indication that indicates that an instance of the IBMzOS_SBInitiatorTargetLogicalUnitPath class has been created.

CIM_IndicationFilter query string:

```
"SELECT * FROM CIM_InstCreation
WHERE SourceInstance ISA
CIM_InitiatorTargetLogicalUnitPath"
```

CIM_InstModification

A life cycle indication that indicates a path state change of an instance of the IBMzOS_SBInitiatorTargetLogicalUnitPath class.

CIM_IndicationFilter query string:

```
"SELECT * FROM CIM_InstModification
WHERE SourceInstance ISA
CIM_InitiatorTargetLogicalUnitPath AND
SourceInstance.CIM_InitiatorTargetLogicalUnitPath::State
<>
PreviousInstance.CIM_InitiatorTargetLogicalUnitPath::State"
```

CIM_InstDeletion

A life cycle indication that indicates that an instance of the IBMzOS_SBInitiatorTargetLogicalUnitPath class has been deleted.

CIM_IndicationFilter query string:

```
"SELECT * FROM CIM_InstDeletion
WHERE SourceInstance ISA
CIM_InitiatorTargetLogicalUnitPath"
```

For more information on how to subscribe to an indication, see “CIM subscription mechanism” on page 289. Specify your queries using the CIM_IndicationFilter query string (see also “CIM_IndicationFilter” on page 290).

Chapter 15. WLM classes

Figure 13 shows the relationship between the IBM extension classes, the IBM extension classes for WLM, and the CIM classes that they extend. The DMTF website provides a detailed description of the CIM classes. The z/OS-specific classes are described in detail in the following chapters.




Figure 13. WLM classes

Figure 14 on page 262 shows a process indication that indicates that a service policy has been activated in the sysplex. This event occurs on each system in the sysplex.




Figure 14. WLM indications

IBMzOS_WLM

Purpose

This class represents the z/OS Workload Manager.

Before you can access this class, be sure that you have prepared the security steps as described in “Setting up the CIM server for WLM management” on page 40

- Grant the requestor's user ID READ access to the RACF facility class MVSADMIN.WLM.POLICY
- If your environment requires program control, be sure that library BLSUXTID in SYS1.MIGLIB is program controlled.

Example:

```

RDEFINE PROGRAM BLSUXTID
RALT PROGRAM BLSUXTID ADDMEM('SYS1.MIGLIB'/'*****'/NOPADCHK) +
UACC(READ)
SETOPTS WHEN(PROGRAM) REFRESH
  
```

Inheritance

CIM_ManagedElement
 ← CIM_ManagedSystemElement
 ← CIM_LogicalElement

← CIM_EnabledLogicalElement
 ← CIM_Service
 ← IBMzOS_WLM

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is
 IBMzOS_WLMProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is
 libwlmprovider.so

Owning component

The z/OS component which owns the CMPI provider is
 WLM

Properties

string Caption	A short description of the class
string Description	A description of the class
string ElementName	Name given to this instance of the class
datetime InstallDate	Not supported
uint16 OperationalStatus[]	The current status of WLM: [2] [OK]
string StatusDescriptions[]	Not supported
string Status	Not supported
uint16 HealthState	The health status of WLM: 5 OK
uint16 EnabledState	Indicates the Enabled or Disabled state: 2 Enabled
string OtherEnabledState	Not supported
uint16 RequestedState	The last requested state: 2 Enabled
uint16 EnabledDefault	Indicates the default value for Enabled State: 2 Enabled
datetime TimeOfLastStateChange	Not supported
string SystemCreationClassName [key]	The scoping system's CreationClassName
string SystemName [key]	The name of the scoping system
string CreationClassName [key]	Indicates the name of the class used in the creation of an instance

string Name [key]	Name of z/OS Workload Management service
string PrimaryOwnerName	Not supported
string PrimaryOwnerContact	Not supported
boolean Started	Indicates if z/OS WLM runs
string ActiveServicePolicy	Name of WLM service policy activated for the sysplex
string PolicyDescription	Description of the WLM service policy activated for the sysplex
datetime PolicyActivationTimestamp	The time the WLM service policy has been activated
string PolicyActivationUser	Userid that activated the WLM service policy
string PolicyActivationSystem	System from which the WLM service policy activation was triggered
string RelatedServiceDefinition	Name of the service definition the WLM service policy was activated from
datetime ServiceDefinitionInstallationTimestamp	Time the service definition was installed
string ServiceDefinitionInstallationUser	User that installed the service definition
string ServiceDefinitionInstallationSystem	System from which the service definition installation was triggered
uint8 ServiceDefinitionFunctionalityLevel	Functionality level of the service definition
string EmbeddedEWLMPolicy	Name of the EWLM policy embedded in the active WLM service policy
datetime EWLMDMPolicyActivationTimestamp	Time the EWLM Domain Manager has triggered the activation of the EWLM policy that is activated on this system
datetime EWLMPolicyActivationTimestamp	Time the EWLM Managed Server has activated the EWLM policy that is activated on this system
datetime EWLMManagementActivationTimestamp	Time when management towards EWLM goals has been activated on this system
boolean PolicyActivationInProgress	Indicates whether a WLM policy activation is currently in progress
boolean AbnormalSystemConfiguration	Indicates an abnormal system configuration

string PolicyActivatingSystem
If a WLM policy activation is currently in progress, the name of the system where the policy activation was triggered

uint8 WLMVersion
WLM version

uint16 CDSFormat
WLM Couple Dataset format

string SysplexMembersSystemName[]
Name of systems in sysplex

uint8 SysplexMembersWLMMode[]
Workload management mode of systems in sysplex:
 0 Undefined
 1 Compatibility Mode
 2 Goal Mode
 3 EWLM Mode

uint8 SysplexMembersWLMStatus[]
Workload management status of systems in sysplex:
 0 Undefined
 1 Initializing
 2 Active
 3 Active, Not Running with Active Policy
 4 Quiesce in Progress
 5 Cleanup Initiated by System
 6 WLM Inactive, Cleanup Complete
 7 Unknown
 8 System Inactive, Cleanup Pending
 9 System Inactive, Cleanup Complete
 10 Unknown

uint8 SysplexMembersGPAStatus[]
Guest platform management provider (GPMP) status of systems in sysplex:
 0 PgmError
 1 Inactive
 2 Started
 3 Active
 4 Connected
 5 Shutdown1
 6 Shutdown2
 7 Shutdown3
 8 Failed
 9 Stopped
 10 SevFailed
 11 Early-IPL
 12 Disabled
 13 Unavailable
 14 Unknown

string SysplexMembersActivePolicy[]
Name of WLM service policy active on systems in sysplex

datetime SysplexMembersPolicyActivationTimestamp[]
Time the WLM service policy was activated on systems in sysplex

string SysplexMembersCleaningSystem[]
If WLM state is 'Cleanup Initiated by System', the name of the system performing the cleanup

string CouplingFacilityStructureNames[]
Name of the WLM coupling facility structures

uint8 CouplingFacilityStructureStatus[]
Status of the WLM coupling facility structures:
0 Disconnected
1 Connected

Methods

uint32 RequestStateChange() Not supported

uint32 StartService() Not supported

uint32 StopService() Not supported

uint32 ActivateServicePolicy()
Activate a service policy contained in the WLM service definition installed in the WLM couple dataset. UPDATE access to the RACF facility class MVSADMIN.WLM.POLICY is required to successfully invoke this method. Successful execution of this method is indicated by an IBMzOS_WLMPolicyActivationIndication indication.

uint32 InstallServiceDefinition()
Install the passed service definition to the WLM couple dataset. UPDATE access to the RACF facility class MVSADMIN.WLM.POLICY is required to successfully invoke this method.

uint32 ExtractServiceDefinition()
Extract the service definition from the WLM couple dataset. READ access to the RACF facility class MVSADMIN.WLM.POLICY is required to successfully invoke this method.

uint32 UploadServiceDefinition()
Save service definition in XML format in a sequential dataset.

uint32 DownloadServiceDefinition()
Download a service definition that is stored in XML format in a sequential dataset.

Indications

IBMzOS_WLMPolicyActivationIndication
A 'process' indication that indicates that a service policy has been activated in the sysplex. This event occurs on each system in the sysplex.

Associations

IBMzOS_WLMOS

Source

IBMzOS_WLM

Target

IBMzOS_ComputerSystem

see

page 267

Association IBMzOS_WLMOS

Purpose

This class associates an IBMzOS_WLM with an IBMzOS_ComputerSystem.

Inheritance

CIM_Dependency

← CIM_HostedDependency

← CIM_HostedService

← IBMzOS_WLMOS

Module name

The module name of the CMPI provider that is registered for a CIM class which is used by the cimprovider command line tool for the administration of CMPI providers is

IBMzOS_WLMOSProviderModule

Provider library

The physical name of a CMPI provider's shared object library as it is stored in the hierarchical file system is

libiwmosProvider.so

Owning component

The z/OS component which owns the CMPI provider is

WLM

Part 5. Developer's guide

Chapter 16. CMPI provider development for z/OS

The system-specific management data for the CIM Schema and system-specific Schema extension classes are provided through management instrumentation. While some management instrumentation is already provided by z/OS CIM (see Chapter 14, “z/OS Management Instrumentation for CIM,” on page 121), it is also possible to develop additional management instrumentation for other z/OS resources which are not accessible through the existing z/OS management instrumentation.

You can implement management instrumentation by developing a provider. A provider is a dynamic load library that implements a given interface and contains the program code used by the CIM server to interact with the system resource described by a certain CIM class, for example CIM_Processor. Providers are registered with the CIM server for a defined CIM class, allowing the CIM server to route all client requests directed against this class to the provider for interacting with the resource. A provider logically acts as an extension of the CIM server for interfacing directly with the managed resources.

Providers are the de facto standard concept for developing management instrumentation, though this purpose of providers is not explicitly mentioned by the various CIM and WBEM standards available from the DMTF. The *Common Manageability Programming Interface* (CMPI) technical standard was defined by The Open Group to allow for developing providers independently from a specific CIM server implementation.

Figure 15 shows the CMPI provider interfaces:




Figure 15. CMPI provider interfaces

CMPI is a C-based programming interface for providers designed for binary compatibility. All management instrumentation included with the z/OS CIM server was developed following the CMPI standard. CMPI is the only supported provider programming interface for the z/OS CIM server. Documentation about the CMPI Technical Standard is available from The Open Group and is not repeated in any documentation available for z/OS. Developers of management instrumentation for

z/OS need to be familiar with the CMPI and CIM/WBEM standards. The information contained here explains the specific aspects that need to be considered for developing CMPI providers for z/OS:

— 1. **Obtain the required header files**

To be able to develop a CMPI provider for z/OS, a set of C header files is required that define the CMPI interface. Due to legal implications with the OpenSource nature of these files, they are not provided together with z/OS CIM, but must be obtained from their original location at The Open Group instead.

Due to the CMPI interface design, you need not link a CMPI provider to any library of the z/OS CIM server. Only the header files are needed for developing a CMPI provider library.

See “Obtaining the required header files” for more information.

— 2. **Follow general aspects of developing a provider**

(see “Following general aspects of developing a provider” on page 273)

— 3. **Expose a provider initialization and function signatures**

(see “Preparing provider initialization and function signatures” on page 274)

— 4. **Consider security aspects**

(see “Planning provider security” on page 275)

— 5. **Convert EBCDIC provider data into UTF-8**

(see “Converting data to ASCII, EBCDIC and UTF-8” on page 276)

— 6. **Follow the guidelines for installing third-party providers**

(see “Provider installation” on page 276)

— 7. **Register the provider with the CIM server**

(see “Registering a provider with the CIM server” on page 277)

— 8. **Optionally use the out-of-process support for providers**

(see “Using the out-of-process support for providers” on page 285)

Obtaining the required header files

Before you can start to develop a provider dynamic load library, you must obtain the following C header files from the OpenPegasus project through the internet:

cmpidt.h	Data type definitions
cmpift.h	Function signature definitions in the form of function tables
cmpimacs.h	CMPI convenience macros (optional)

These files are available in the OpenPegasus CVS Repository. Users familiar with CVS can check out these files using a CVS client on any platform by following the instructions on the OpenPegasus website in the “CVS Overview” section. The required files are located in directory `pegasus/src/Pegasus/Provider/CMPI`. To get the correct version of the files, they need to be checked out with at least the `RELEASE_2_8_1` tag.

If you are not familiar with using CVS, obtain the files through a web browser starting at the OpenPegasus website. You can navigate from the “Web CVS” section to the required CMPI files by clicking on the following directory names (see also Figure 16 on page 273):

`pegasus → src → Pegasus → Provider → CMPI`

OpenPegasus CVS Repository











File
 Attic/ [show contents]
 atlas/
 cvstest/
 deleteme/
 dmtfdocs/
 junk/
 pegasus/
 pegasus-JavaCIMClient/
 pegasus_unsupported/
 xxxx/

Figure 16. OpenPegasus CVS Repository

Once you have successfully navigated to the CMPI directory, the required header files are at the end of the list of displayed files. To get the correct version of the files, select the tag `RELEASE_2_8_1` or above from the list.

To download the files, first click on the version number displayed in the column after each file name and then select **download** on the next screen where the content of the file is displayed. Once you have successfully downloaded the files, transfer them to the z/OS system on which the provider dynamic load library will be developed, ideally to a ZFS directory. Please note that when transferring files from the workstation to a z/OS system, they should be converted from ASCII to EBCDIC encoding.

There are also a couple of samples for CMPI providers available on the OpenPegasus CVS Repository. They can be obtained the same way as the header files by navigating to the `pegasus/src/Providers/sample/CMPI` directory.

Following general aspects of developing a provider

Before you can start to develop a CMPI provider, you first need to have the CIM class model containing descriptions for the resource to be instrumented in the form of a CIM class. Follow the WBEM standards, and in particular be consistent with the CIM Schema supported by the CIM server when you develop the CIM class. Usually, a CIM class for which a provider is written, is derived from one of the classes in the CIM Schema provided by the DMTF, and named with a vendor-specific class name prefix. For example, the prefix `"IBMzOS_"` is used for all classes provided by IBM for the z/OS operating system. This naming scheme also helps to prevent conflicts with the resources that have already been instrumented for CIM by IBM or other vendors.

Note: In general it is not recommended to create new providers for resources that have already been instrumented by IBM.

I Preparing provider initialization and function signatures

The nature of a CMPI provider does not require static linking to any of the CIM server's libraries. Instead, for each provider function group a single initialization routine (factory) entry point must be exposed following a defined naming scheme, so that the CIM server can call this entry point by name once it has dynamically loaded a provider dynamic load library. The CIM server will attempt to determine the function groups supported by a provider and the respective entry points by verifying the existence of the according provider factory entry points.

The signature for the factory functions looks like this:

```
CMPI<mi-type>MI * <mi-name>_Create_<mi-type>MI(CMPIBroker*,
                                                CMPIContext*,
                                                CMPIStatus*);
```

where <mi-type> refers to the function group of the provider, and <mi-name> refers to the actual provider name as specified during provider registration.

Important:

The actual signature of this function has an additional '_' after '_Create', which is not described as such in the initial version of the CMPI Technical Standard, but is changed in a corrigendum to match the existing implementations of the CMPI interface.

The factory function must return a pointer to a valid CMPI<mi-type>MI structure, where the major component of this structure is the table holding the function pointers, and thus enabling access to the individual provider group functions for the CIM server. An example of such a function pointer is the pointer to the *enumerateInstances* function in the CMPIInstanceMI structure.

The function groups for CMPI providers are *Instance*, *Association*, *Property*, *Method* or *Indication*, where type *Property* is not supported by the z/OS CIM server.

In file *cmpimacs.h*, a set of C preprocessor macros is defined that you may use for the provider initialization code and through which the required code for the <mi-name>_Create_<mi-type>MI function is generated in a convenient way. These macros are called *CM<mi-type>MIStub* and they are used in many of the examples referenced in "Samples" on page 285.

For further details refer to "MI Factories" in *CMPI Technical Standard Document* provided by The Open Group.

For each of the CMPI provider function groups, a set of C functions must be implemented as described in "MI Function Signatures" of the *CMPI Technical Standard Document*.

Instance provider functions

Instance providers are the most common kind of management instrumentation. They implement the basic access to the resources described in a CIM class. With an instance provider it is possible to create, enumerate, modify, delete, query or simply retrieve system resources:

- cleanup(...)
- enumInstanceNames(...)

- enumInstances(...)
- getInstance(...)
- createInstance(...)
- modifyInstance(...)
- deleteInstance(...)
- execQuery(...)

Method provider functions

Method providers are needed to implement the methods defined for a CIM class.

- cleanup(...)
- invokeMethod(...)

Association provider functions

Association providers are needed to implement the relationships between system resources as defined by the association classes.

- cleanup(...)
- Associators(...)
- AssociatorNames(...)
- References(...)
- ReferenceNames(...)

Indication provider functions

Event or indication providers must be implemented for event subscription and notification:

- cleanup(...)
- AuthorizeFilter(...)
- MustPoll(...)
- ActivateFilter(...)
- DeActivateFilter(...)
- EnableIndications(...)
- DisableIndications(...)

Please note that the function *MustPoll* is not supported for z/OS.

Planning provider security

When developing a CMPI provider for z/OS, consider the security context in which the provider runs. Besides the levels of security provided by the z/OS CIM server for authentication and authorization, a provider is processed in the context of a user ID:

Requestor's user ID

By default, a provider is processed in the context of the requestor's user ID for all invocations that are caused by an external CIM operation. This means that the provider runs under the identity of the requestor's user ID, and resource access authorization occurs against this user ID. See the usage notes for the `pthread_security_np` call in "Callable services descriptions" in *z/OS UNIX System Services Programming: Assembler Callable Services Reference* for additional information.

Designated user ID

Alternatively, you can provide a designated user ID that runs the provider.

Specify the designated user ID during provider registration using the *UserContext* and *DesignatedUserContext* properties of the *PG_ProviderModule* class.

When a provider is registered with a designated user ID, the CIM server processes all requests under the designated user ID, regardless which client user ID has issued the request.

The user ID of the requestor is still available for the provider and should be used for further authorization checking in order to prevent unauthorized access to a resource. You have to specify similar security definitions for the designated user ID as for regular client users, as described in “Switching identity (surrogate)” on page 29.

Converting data to ASCII, EBCDIC and UTF-8

Character encoding in the CIM over HTTP protocol is done using UTF-8 character encoding. For that reason CIM clients expect valid UTF-8 returned by the CIM server. The z/OS CIM server executes in the Enhanced ASCII mode. This means that all string data within the CIM server's address space is represented in ASCII rather than EBCDIC encoding. For a provider this means that all string data exchanged with the CIM server is expected to be in ASCII (codepage ISO/IEC 8859-1), encoded in UTF-8 format. Since the native data of z/OS resources is usually represented in EBCDIC, the provider code needs to convert this data before it can return it to the CIM server through the CMPI interface, or when it receives data from the CIM server through the CMPI interface.

UTF-8 is a multi-byte character encoding for UNICODE which can represent much more characters than EBCDIC. While no issue on returning data from a provider through the CIM server to a client, the range of input characters from a client can be larger than a provider can represent in EBCDIC. All valid (7-bit) ASCII characters are also valid UTF-8. Please note that a transformation of the character encoding from EBCDIC to ASCII can generate invalid ASCII, that is ASCII-code above the 7-bit margin.

Therefore it is recommended to compile the provider's C code using the ASCII option of the z/OS XL C/C++ compiler. Using the ASCII option also requires the XPLINK compile and link option.

See *Appendix B* in the *z/OS XL C/C++ Run-Time Library Reference* for additional information about the Enhanced ASCII support. Also see the *z/OS XL C/C++ Guide* and the *z/OS XL C/C++ Programming Guide* for details about the ASCII compiler option.

Provider installation

To enable the CIM server to find and load provider modules and related modules, a provider has to be stored in the hierarchical file system and the CIM server run-time environment has to be tailored. A CMPI provider for z/OS consists of provider modules, dependent modules, the CIM Schema extensions (MOF), and the CMPI provider registration information (MOF).

Installing providers and dependent load modules

When you develop a CMPI provider, you ship a provider module, a dynamic load library (DLL) module, and, if applicable, its dependent libraries.

- We recommend to store the provider DLL and its dependent libraries in a separate hierarchical file system directory, such as */usr/lpp/myProd/provider*.
- On systems where program control is enabled, flag the provider DLL and its dependent libraries as program controlled using the `extattr` UNIX System Services command:

```
extattr +p <providerfile>
```

We recommend to flag all modules as program controlled by default.

More information:

"Defining modules to program control" in *z/OS UNIX System Services Planning*

Customizing the CIM server environment for third-party providers

- To enable the CIM server to locate the provider module, extend the CIM server's search list for provider directories by setting the *providerDir* configuration property, such as

```
providerDir=/usr/lpp/wbem/lib:/usr/lpp/wbem/provider:/usr/lpp/myProd/provider
```

More information: Chapter 9, "CIM server configuration," on page 53
- To locate the provider dependent libraries, extend the library search path (LIBPATH) for the CIM server.
 - The default library search path for the CIM server is defined in the file */etc/wbem/cimserver.env* for the started task CFZCIM. Add your installation directory to the LIBPATH, for example:

```
LIBPATH=/usr/lpp/wbem/lib:/usr/lpp/wbem/provider:/usr/lib:  
/usr/lpp/myProd/provider
```
 - If you run the CIM server and tools from the UNIX System Services shell, extend the LIBPATH of the shell.

Registering a provider with the CIM server

When the provider dynamic load library has been made physically accessible to the CIM server, it needs to be registered via a special MOF file using the `cimmo` command. A provider registration MOF file contains instances of the CIM classes from the provider registration schema, namely of classes `PG_ProviderModule`, `PG_Provider` and `PG_ProviderCapabilities` as shown in Figure 17 on page 278.




Figure 17. CIM classes from the provider registration schema

The instances of these classes contain all the information that the CIM server needs to know about a provider, for example its physical packaging structure, supported CIM classes and namespaces, as well as the set of supported provider operations.

Once the provider registration MOF file has been created with the instances of classes PG_Provider, PG_ProviderModule and PG_ProviderCapabilities, the content of this MOF file can be loaded into the CIM server's root/PG_InterOp namespace using the cimmoF command.

The cimmoF command stores this information in the CIM server run-time repository.

Example:

```
cimmoF -n root/PG_InterOp TestProviderRegistration.mof
```

The CIM server automatically migrates the repository from one z/OS version to the next. This means, that once the additional provider MOFs have been installed, there is no need to install them again after a z/OS release upgrade.

| If the run-time repository including your definitions has been deleted and the CIM
| server master repository has to be restored, your CIM Schema extensions and
| provider registration are lost and you have to register them again.

| Therefore these MOF files should be part of your delivery and stored in your
| hierarchical file system directory, such as for example:

| */usr/lpp/myProd/schemas*

| stores the schema descriptions and registration information

| *MYPROD_ClassName.mof*

| contains the CIM Schema description

| *MYPROD_ClassNameRegistration.mof*

| contains the provider registration

More information:

“cimmof” on page 77

“PG_Provider” on page 280

“PG_ProviderModule” on page 281

“PG_ProviderCapabilities” on page 283

PG_Provider

Purpose

This class is the logical representation of a CIM provider. Its only properties are the name of the provider, the name of the provider module in which the code of the provider physically resides and the name of a SAF security profile to be checked before a client is granted access to the provider.

Properties

- | | |
|-------------------------------------|--|
| string ProviderModuleName | The name of the provider module containing the code for this provider. This name needs to match the value of the <i>Name</i> property of the corresponding instance of class PG_ProviderModule. |
| string Name | The name of the provider. This name is used to identify a specific provider within a provider module (dynamic load library) and specifies the prefix of a provider's <i>_Create_<mi-type>MI()</i> initialization function. |
| string SecurityAccessProfile | <p>This property defines the name of a z/OS security server's profile in the CIM server's WBEM class that will be checked for a requestor's access before a request is routed to this provider. Depending on the type of the CIM operation, a different level of access to the security profile is required as listed in Table 2 on page 28.</p> <p>This is not a required property and can be omitted from the provider registration MOF.</p> |

Examples

Example of an instance of class PG_Provider in MOF syntax:

```
instance of PG_Provider
{
    //The provider module as defined in PG_ProviderModule
    ProviderModuleName = "TestClassProviderModule";
    // The provider name as referenced in the code
    Name = "TestClassProvider";
};
```

PG_ProviderModule

Purpose

This class represents the physical packaging of one or more providers in a dynamic load library or shared library.

Properties

string Name	The logical name of the provider module.
string Vendor	The name of the provider module vendor, for example, IBM.
string Version	The provider module version.
string InterfaceType	The interface type implemented by the provider. Must be CMPI for z/OS.
string InterfaceVersion	The interface version number implemented by the provider. Must be 2.0.0 for CMPI on z/OS.
string Location	<p>The name of the dynamic load library or shared library in the hierarchical file system without a path name. The name specified for <i>Location</i> is automatically prefixed with <i>lib</i> and extended with <i>.so</i> by the CIM server:</p> <p><code>lib<Location>.so</code></p>
boolean ShareAS	<p>Setting the <i>ShareAS</i> property to false causes the provider module to run in its own copy of a provider agent process. No other provider module will be loaded into this process.</p> <p>Setting the <i>ShareAS</i> property to false has a major impact on the performance, so you should not set it to 'false' unless there is an urgent need for a provider module to be protected from other provider modules. The default setting of <i>ShareAS</i> is true.</p> <p>Setting <i>ShareAS</i> to false is only honored by the CIM server, if it is running with the configuration property <i>forceProviderProcesses</i> set to true.</p>
uint16 UserContext	<p>Defines the user context in which this provider module is invoked.</p> <p>Values:</p> <p>2 (Requestor), default</p> <p>The provider is invoked in the security context of the user requesting an operation.</p> <p>3 (Designated User)</p> <p>The provider is invoked in the security context of the user ID specified by the <i>DesignatedUserContext</i> property.</p> <p>See "Running providers in a designated user context" on page 42 for a general description on running a provider module with a designated user context.</p>

string DesignatedUserContext

Specifies the user ID providing the context in which this provider module is invoked (regardless of which user requests an operation).

Values:

NULL when *UserContext* = 2

non-NULL value
 when *UserContext* = 3

See "Running providers in a designated user context" on page 42 for a general description on running a provider module with a designated user context.

string ModuleGroupName

Specifies a group name for the provider module, if the configuration property *forceProviderProcesses* is true. Else it has no effect.

This property controls which provider modules are running together in the same provider agent process.

- If the specified value is *CIMServer*, the provider module is loaded into the CIM server process.
- Provider modules having the same group name other than *CIMServer* are loaded into a single agent process.
- If no module group name is defined, the provider either runs in a single shared provider agent process together with all other providers without a module group name, or in its own distinct provider agent process in case *ShareAS* is true.

Can be set dynamically using the *cimprovider* command (see "cimprovider" on page 81).

Examples

Example of an instance of class *PG_ProviderModule* in MOF syntax:

```
instance of PG_ProviderModule
{
    Name = "TestClassProviderModule";
    //The library name on disk
    Location = "TestClassProvider";
    // (will be extended to libTestClassProvider.so)
    Vendor = "IBM";
    Version = "1.0.0";
    InterfaceType = "CMPI";
    InterfaceVersion = "2.0.0";
    ShareAS = true;
    UserContext = 2;
};
```

PG_ProviderCapabilities

Purpose

This class describes the specific capabilities of a provider. Multiple instances of PG_ProviderCapabilities can be created for each provider allowing the same provider to be registered, for example, for multiple CIM classes.

Properties

string ProviderModuleName	The name of the provider module as specified in the corresponding instances of classes PG_Provider and PG_ProviderModule.
string ProviderName	The name of the provider as specified in the corresponding instance of class PG_Provider.
string CapabilityID	A value that uniquely identifies this <i>Capabilities</i> instance within the set of <i>Capabilities</i> for the designated provider.
uint16[] ProviderType	Enumerates the kind of provider capabilities (=supported operations) defined for the associated provider: 2 Instance 3 Association 4 Indication 5 Method 6 IndicationConsumer (not supported for z/OS) 7 InstanceQuery
string ClassName	Describes the CIM class for which the associated provider supplies instances, associations or indications information.
string[] Namespaces	Describes the namespaces that are supported by the provider for this CIM class.
string[] SupportedProperties	Lists the properties supported by this provider. If this array is empty, the provider must support all of the properties defined in the class.
string[] SupportedMethods	Lists the methods supported by this provider. If this array is empty, the provider must support all the methods defined in the class.

Examples

Example of an instance of class PG_ProviderCapabilities in MOF syntax:

```
instance of PG_ProviderCapabilities
{
    //The provider module as defined in PG_ProviderModule
    ProviderModuleName = "TestClassProviderModule";
    //The provider name as defined in PG_Provider
    ProviderName = "TestClassProvider";
    CapabilityID = "1";
    //Name of the CIM class as defined in the mof
    ClassName = "IBMzOS_TestClassB";
    Namespaces = {"root/cimv2","root/test"};
    ProviderType = { 2, 5 }; // Instance, Method
    SupportedProperties = NULL; // All properties
    SupportedMethods = NULL; // All methods
};
```

```

instance of PG_ProviderCapabilities
{
    //The provider module as defined in PG_ProviderModule
    ProviderModuleName = "TestClassProviderModule";
    //The provider name as defined in PG_Provider
    ProviderName = "TestClassProvider";
    CapabilityID = "2";
    //Name of the CIM class as defined in the mof
    ClassName = "IBMzOS_TestIndication";
    Namespaces = {"root/cimv2"};
    ProviderType = { 4 }; // Indication
    SupportedProperties = NULL; // All properties
    SupportedMethods = NULL; // All methods
};

```

Using the out-of-process support for providers

When the CIM server is started in out-of-process mode using the *forceProviderProcesses* configuration property, providers may run in separate address spaces. Then, the z/OS-specific property *ShareAS* and the common property *ModuleGroupName* for class *PG_ProviderModule* are considered. You may specify them during provider registration via the registration MOF file. *ModuleGroupName* can also be set dynamically at runtime using the -g option of the *cimprovider*.

To specify that a provider shall always run in its own provider agent process,

- set the z/OS-specific property *ShareAS* to false during provider registration.

To define a group of providers sharing a provider agent process,

- assign the same module group name to the respective providers using the property *ModuleGroupName* during provider registration.

To specify that a provider shall run in the CIM server address space,

- assign the module group name *CIMserver* to the property *ModuleGroupName* of the provider during provider registration.

Example of a provider registration MOF file with properties specified for the out-of-process support:

```
instance of PG_ProviderModule
{
    Name = "OSBase_TestClassProviderModule";
    //The library name on disk
    Location = "cmpiOSBase_TestClassProvider";
    Vendor = "IBM";
    Version = "2.0.0";
    InterfaceType = "CMPI";
    InterfaceVersion = "2.0.0";
    ShareAS = false;
    ModuleGroupName = "CMPITEST";
};
```

Samples

Examples for CMPI providers can be found on the *OpenPegasus CVS Repository*, located in the *pegasus/src/Providers/sample/CMPI* directory. You can access them in the same ways as described in “Obtaining the required header files” on page 272. Please note that these examples have been enabled for z/OS only in an OpenPegasus build environment and will need some minor adoptions for a custom build environment.

Additional examples are available from the *SBLIM OpenSource* project (packages *sbim-cmpi-<xxx>*) hosted on SourceForge.net. Although the CIM providers from SBLIM apply to Linux platforms only, they are examples for how to write CIM providers in general. The SBLIM project also provides a number of useful tools and documents related to provider development.

Chapter 17. CIM indications

Indications in CIM are represented as instances of class CIM_Indication. This abstract class serves as the base class for all indication classes.

Indications are transient instances used to distribute information from an indication generator to an arbitrary number of indication consumers. Therefore, they are typically very short-living. Indications have a source namespace, this is the value of the *SourceNamespace* property of the CIM_IndicationFilter instance that produced the indication. Although indications are instances of CIM classes, they are unique in that they cannot be addressed, but can only be received by subscription. Hence, indication instances cannot be enumerated, created, deleted, retrieved or modified by client operations.

Note that z/OS does not ship generic providers, that is, an indication subscription is only processed if the required indication provider exists and is registered with the CIM server for a certain CIM resource class.

The CIM Schema version provided with z/OS supports two types of indications (representing different types of events) which are modeled as CIM_Indication subclasses. These subclasses include:

CIM_InstIndication

used to report life cycle events for CIM instances. Types of events include: Instance creation, deletion, modification, method invocation and read access. For each of these types, a specific subclass of CIM_InstIndication is defined in the CIM Schema: CIM_InstCreation, CIM_InstDeletion, CIM_InstModification, CIM_InstMethodCall and CIM_InstRead. Only the first three are currently supported for z/OS.

CIM_ProcessIndication

used to report the occurrence of any other event, typically alert type events. See “CIM_ProcessIndication” on page 288.




Figure 18. z/OS CIM indication hierarchy

CIM indication class hierarchy

The CIM indication class hierarchy models the types of events that can be detected. An instance of **CIM_Indication** represents the occurrence of an event in general. Indication instances cannot be addressed, but they have a source namespace. Although indications are modeled using CIM classes, indications are unique in that they cannot be manipulated or retrieved, but they can only be received by subscription. The **CIM_Indication** class is the base class for all other indication classes. It includes the following properties:

IndicationIdentifier

identifies indication instances uniquely within their source namespace.

IndicationTime

describes, to the extent possible, the time and date of the creation of the underlying event for the indication.

CorrelatedIndications

specifies a list of other indications, referenced by their *IndicationIdentifier* property values, that are related to this indication. These *IndicationIdentifier* property values are interpreted to have the same source namespace as this indication.

While the *CorrelatedIndications* property values are to be interpreted in the context of a single CIM namespace, any instances of other classes of the CIM Event Model do not need to be located in the same namespace.

CIM_ProcessIndication

CIM_ProcessIndication models any events other than life cycle events. In the CIM Schema version supported for z/OS, the following two subclasses of **CIM_ProcessIndication** are defined:

- **CIM_AlertIndication** – signals the occurrence of an alert type of event. Properties of this subclass include *PerceivedSeverity*, *ProbableCause*, *RecommendedAction* and *Trending*, describing an alerting situation.

- CIM_SNMPTrapIndication – used to map SNMP traps to CIM indications. This is currently not supported by the z/OS CIM server.

CIM_InstIndication (Lifecycle Event)

An instance of CIM_InstIndication denotes the occurrence of a life cycle event on a CIM instance. The possible life cycle events are: creating an instance, deleting an instance, modifying an instance, reading an instance or invoking a CIM method on an instance. An instance of CIM_InstIndication includes an embedded copy (that is, a current snapshot) of the instance, SourceInstance, on which the life cycle event occurred.

Instances of CIM_InstModification include an embedded copy of the instance, PreviousInstance, before the modification occurred.

Lifecycle events on CIM instances include both, changes caused by a CIM client, and changes that happen spontaneously from a CIM client perspective due to volatile behavior of the CIM provider.

CIM_InstModification

Lifecycle events on CIM instances include both, changes caused by a CIM client, and changes that are caused by a change of the underlying system resource that is represented via a CIM instance.

CIM subscription mechanism

The CIM Event Model defines how CIM clients subscribe to receive indications as shown in Figure 19 and Figure 20 on page 291. A CIM_IndicationFilter instance describes the set of conditions, a CIM_ListenerDestinationCIMXML instance defines the *CIM listener* and the communication protocol, that is, it describes the method and targets for distributing the indications. Finally, a CIM_IndicationSubscription association instance between the CIM_IndicationFilter instance and the CIM_ListenerDestinationCIMXML instance is used to subscribe for receiving these indications. The creation of this association instance activates the subscription.




Figure 19. Indication subscription class diagram

CIM_IndicationFilter

An instance of CIM_IndicationFilter describes the set of indications of interest by means of a query expression. This is also called the desired indication stream. The most relevant properties of CIM_IndicationFilter are:

- **Name, CreationClassName, SystemName, SystemCreationClassName** – key properties.
- **SourceNamespace** – defines the source namespace for the indications resulting from this indication stream.
- **Query** – query string, like “select * from CIM_InstModification where ...”; defines the indication class, filter condition and property list of the indication stream.
- **QueryLanguage** – defines the query language used in the **Query** property. The z/OS CIM server supports the query languages “DMTF:CQL” (CIM Query Language) and “WQL” (WBEM Query Language). For more information, see the CIM Query Language Specification.
- **DeliveryRetryInterval** defines the minimum time between two delivery retries.
- **DeliveryRetryAttempts** defines the maximum number of delivery retries.

For information about the complete set of properties of a CIM_IndicationFilter, refer to the CIM Event Model White Paper or to the definition of this class in the CIM Schema. The white paper also contains an example of a CIM_IndicationFilter instance.

CIM_ListenerDestinationCIMXML

An instance of CIM_ListenerDestinationCIMXML defines “how and where” to send an indication. In particular, the CIM_ListenerDestinationCIMXML instance defines the desired indication destination, encoding and protocol for delivery of the indication stream. CIM_ListenerDestinationCIMXML specializes CIM_ListenerDestination and is used for indication consumers that support the CIM Operations over HTTP protocol (see Specification for CIM Operations over HTTP, DSP0200, on <http://www.dmtf.org/standards/documents/WBEM/DSP200.html>).

The CIM_ListenerDestination class hierarchy can be extended to allow the definition of additional indication handling mechanisms.

The most relevant properties of CIM_ListenerDestinationCIMXML are:

- **Name, CreationClassName, SystemName, SystemCreationClassName** – key properties
- **Destination** – URL to which the indications are to be delivered

For information about the complete set of properties of CIM_ListenerDestinationCIMXML, refer to the CIM Event Model White Paper or to the definition of this class in the CIM Schema.




Figure 20. Indication Handler

CIM_IndicationSubscription

Primarily, an instance of `CIM_IndicationSubscription` defines the association between a `CIM_IndicationFilter` instance and a `CIM_ListenerDestinationCIMXML` instance. In addition, it includes a set of properties that further specify the behavior of a subscription. The most relevant properties of `CIM_IndicationSubscription` are:

- The **Repeat Notification** properties (those having "RepeatNotification" contained in their property name) define the behavior for handling indications that report the occurrence of the same underlying event (that is, the disk is still generating I/O errors and has not yet been repaired).
- The **Subscription State** properties (those having "SubscriptionState" contained in their property name) allow a CIM client to monitor and control the state of the subscription.
- The **Subscription Failure Handling** properties (`OnFatalErrorPolicy`, `OtherOnFatalErrorPolicy`, `FailureTriggerTimeInterval`) define the desired behavior when a fatal error occurs during subscription processing.
- The **Subscription Duration** properties (`SubscriptionDuration`, `SubscriptionStartTime`, `SubscriptionTimeRemaining`) allow to expire a subscription automatically, based upon elapsed time since its creation, and to monitor the elapsed times since creation and until expiration.

You can find more detailed information about these properties as well as the complete set of properties of `CIM_IndicationSubscription` in the CIM Event Model White Paper or in the definition of this class in the CIM Schema.

Part 6. Messages

Chapter 18. z/OS specific messages

Messages are written into the appropriate logs and also displayed at the z/OS console.

All messages issued by the CIM server are part of the underlying OpenPegasus code. This section documents only those messages that are specific while using the CIM server on z/OS, together with explanation, system action, (system) programmer and user response.

All other OpenPegasus messages are wrapped by one of the following generic z/OS messages.

CFZ00001I for INFORMATION log messages
CFZ00002W for WARNING log messages
CFZ00004E for SEVERE and FATAL log messages

CEZ-prefix messages

CEZ02000I Requesting CONFIG ONLINE for CPU
CPU-address

Explanation: The IBMzOS_Processor method RequestStateChange has been issued with RequestedState=Enabled.

System action: None.

System programmer response: Issue a CF CPU(*CPU-address*),ONLINE command, or use your automation tool to set the CPU *CPU-address* online.

User response: None.

CEZ02001I Requesting CONFIG OFFLINE for CPU
CPU-address

Explanation: The IBMzOS_Processor method RequestStateChange has been issued with RequestedState=Offline.

System action: None.

System programmer response: Issue a CF CPU(*CPU-address*),OFFLINE command, or use your automation tool to set the CPU *CPU-address* offline.

User response: None.

CEZ03000E Request user ID *user-ID* requires
UPDATE permission on profile
IOSCDR CL(FACILITY).

Explanation: A CIM operation was invoked that requires the use of an authorized IOSCDR service. The IOSCDR service is used by CIM providers to retrieve device identification information (such as the serial

number and the model number) for an I/O device. Providers that instrument the CIM classes IBMzOS_SBProtocolEndpoint or IBMzOS_SBInitiatorTargetLogicalUnitPath are an example for this scenario.

System action: The requested CIM operation is returned in error.

System programmer response: Verify if the user should be permitted to perform operations using the IOSCDR service. If so, grant the user *user-ID* UPDATE permission to the profile IOSCDR in the class FACILITY. Then restart the CIM server.

User response: Report this problem to your system programmer.

| **CEZ03001E** Internal error occurred. SMI-S
| Indication Data Cache error *error-code*.

| **Explanation:** The SMI-S data cache and thread are in
| an unrecoverable error state. *error-code* describes the
| kind of error.

| **System action:** The requested CIM operation is
| returned in error.

| **System programmer response:** The error code
| indicates the kind of error:
| 1 (SMIS_CACHE_CONTROL_ERROR)
| Error in the data cache control structures
| 2 (SMIS_CACHE_ERROR)
| Error in the data cache data
| 3 (SMIS_THREAD_CREATION_ERROR)
| Error in data cache thread

| Restart the CIM server. If the problem persists, contact IBM service for assistance.

| **User response:** Report this problem to your system programmer.

| **CEZ03002W Lost connection to CEA, trying to reconnect. CIM Indications may get lost.**

| **Explanation:** The SMI-S CIM indication provider has lost the connection to CEA. Without this connection, no SMI-S CIM indications can be generated, for example for changes on port controllers.

| **System action:** The CIM provider continuously attempts to reconnect to CEA until it becomes available.

| **System programmer response:** Restart Common Event Adapter (CEA) in full function mode.

| **User response:** Report this problem to your system programmer.

| **CEZ03003W Failed to reconnect to CEA. CIM Indications may get lost.**

| **Explanation:** The SMI-S CIM indication provider failed to reconnect to CEA. Without this connection, no SMI-S CIM indications can be generated, for example for changes on port controllers.

| **System action:** The CIM provider continuously attempts to reconnect to the CEA until it becomes available.

| **System programmer response:** Restart Common Event Adapter (CEA) in full function mode.

| **User response:** Report this problem to your system programmer.

| **CEZ03004I Successfully reconnected to CEA.**

| **Explanation:** The SMI-S CIM indication provider has successfully reconnected to CEA.

| **System action:** None.

| **System programmer response:** None.

| **User response:** None.

| **CEZ03005I Successfully re-established subscription to CEA.**

| **Explanation:** The SMI-S CIM indication provider has successfully renewed its subscriptions for ENF signals to CEA.

| **System action:** None.

| **System programmer response:** None.

| **User response:** None.

| **CEZ03006E Subscription to CEA failed for handler *module-name* with reason code *reason-code*.**

| **Explanation:** The SMI-S CIM indication provider failed to subscribe to CEA in order to receive ENF signals through CEA subscription handler *module-name*.

| **System action:** The requested CIM operation is returned in error.

| **System programmer response:** The *reason-code* indicates why the CEA subscription to handler *module name* failed. See "Appendix C. CEA reason codes" on page 339 for error details. After correcting the error, restart the CIM server.

| **User response:** Report this problem to your system programmer.

| **CEZ03007E Failed to retrieve CEA event, reason code *reason-code*.**

| **Explanation:** The SMI-S CIM indication provider failed to receive a CEA event and therefore cannot process CIM indications.

| **System action:** None.

| **System programmer response:** See "Appendix C. CEA reason codes" on page 339 for error details. After correcting the error, restart the CIM server.

| **User response:** Report this problem to your system programmer.

| **CEZ03008W Renewing CEA subscription after operator unsubscribe.**

| **Explanation:** The SMI-S CIM indication provider has detected an operator forced unsubscribe from CEA. Since this would leave orphaned CIM indication subscriptions, the subscription to CEA is automatically re-established.

| **System action:** The SMI-S CIM provider automatically re-establishes the removed CEA subscriptions.

| **System programmer response:** Remove SMI-S CIM subscriptions through the *cimsub* utility (see "*cimsub*" on page 110) or make sure the CIM clients are properly unsubscribed from SMI-S CIM indications for this system.

| **User response:** Report this problem to your system programmer.

| **CEZ03009W Missed CEA event(s) caused loss of CIM indications.**

| **Explanation:** The SMI-S CIM indication provider was informed by the Common Event Adapter (CEA) that it has missed a number of events. This causes a loss of CIM indications for subscribed CIM Client applications.

| **System action:** None.

| **System programmer response:** None.

| **User response:** If known, inform the owners of CIM client applications that have subscribed to this z/OS system.

| **CEZ03010E** User *user-ID* not authorized to connect to Common Event Adapter (CEA).

| **Explanation:** The user *user-ID* is not authorized to connect to the Common Event Adapter (CEA). The CIM SMI-S indication providers depend on CEA for issuing indications about state changes related to FC Ports. After correcting the error, restart the CIM server.

| **System action:** None.

| **System programmer response:** Ensure that the user *user-ID* has READ access to profile CEA.CONNECT in the SERVAUTH class.

| See "Setting up the CIM server for storage management" on page 41 for the authorizations required to connect to CEA.

| **User response:** Contact your system programmer or security administrator.

| **CEZ03011E** User *user-ID* not authorized for subscription to Common Event Adapter (CEA).

| **Explanation:** The user is not authorized to subscribe for ENF signals through the Common Event Adapter (CEA). The CIM SMI-S indication providers depend on the CEA for issuing indications about state changes.

| **System action:** None.

| **System programmer response:** Ensure the user *user-ID* has READ access to profiles

- | • CEA.SUBSCRIBE.ENF_0009*
- | • CEA.SUBSCRIBE.ENF_0027*
- | • CEA.SUBSCRIBE.ENF_0033*

| in the SERVAUTH class.

| See "Setting up the CIM server for storage management" on page 41 for the authorizations required to connect to CEA. After correcting the error, restart the CIM server.

| **User response:** Contact your system programmer or security administrator.

| **CEZ03012E** Connection to CEA failed with reason code *reason-code*.

| **Explanation:** The SMI-S CIM indication provider failed to connect to the Common Event Adapter and therefore cannot process CIM indications.

| **System action:** CIM Indications for SMI-S are unavailable.

| **System programmer response:** See "Appendix C. CEA

| reason codes" on page 339 for error details. After correcting the error, restart the CIM server.

| **User response:** Contact your system programmer.

| **CEZ05000E** Internal error detected in provider module *module-name* when method *method-name* invoked system service *service-name*. The service returned RC=*return-code* RSN=CEA-*reason-code*. Additional diagnostic information: CEAERRO_Diag1=*code1* CEAERRO_Diag2=*code2* CEAERRO_Diag3=*code3* CEAERRO_Diag4=*code4* CEAERRO_Msg=*text*

Explanation: The system encountered an internal error while processing a CIM request. The following information is provided:

module-name

Name of CIM provider module

method-name

Name of CIM method invoked

service-name

Name of the internal service, usually in the CEA component

return-code

Internal return code

CEA-reason-code

Internal CEA reason code. See "Appendix C. CEA reason codes" on page 339 for details.

CEAERRO_Diag1-4

Internal values representing errors in system processing on behalf of the CIM request

CEAERRO_Msg

Textual information saved by system processing on behalf of the CIM request

System action: System processing ended with the error information described in this message.

System programmer response: See CEAERRO_Msg for more informational messages about the problem. If the problem is still unclear or no additional messages are available, contact IBM Service for assistance.

User response: Report this problem to your system programmer.

| **CEZ05001E** Internal error detected in provider module *module-name* when method *method-name* invoked system service *service-name*. The service returned RC=*return-code* RSN=CEA-*reason-code*

Explanation: The system encountered an internal error while processing a CIM request. The following information is provided:

module-name

Name of CIM provider module

method-name

Name of CIM method invoked

service-name

Name of the internal service, usually in the CEA component

return-code

Internal return code

CEA-reason-code

Internal CEA reason code. See "Appendix C. CEA reason codes" on page 339 for details.

System action: The requested CIM operation is returned in error. System processing ended with the error information described in this message.

System programmer response: Contact IBM Service for assistance.

User response: Report this problem to your system programmer.

CEZ05002E Common Event Adapter (CEA) not available.

Explanation: A CIM method was invoked, but the CEA address space was not active to process the request.

System action: The requested CIM operation is returned in error.

System programmer response: Enter the command START CEA from the operator console to start the CEA address space. Verify that CEA is active through the command D A,CEA.

User response: Report this problem to your system programmer.

CEZ05003E User *user-name* not authorized for Common Event Adapter (CEA) request.

Explanation: A CIM method was invoked, but the user is not authorized to issue requests to the CEA component.

System action: The requested CIM operation is returned in error.

System programmer response: Ensure that the user has access to CEA. Refer to "RACF setup" on page 39.

User response: Report this problem to your system programmer.

CEZ05004E IPCS Sysplex Dump Directory cannot find incident information.

Explanation: A CIM method was invoked to locate a specific incident, but the Common Event Adapter (CEA) component cannot locate the incident in the sysplex dump directory (SYS1.DDIR). Common reasons include:

- Sysplex dump directory SYS1.DDIR (or equivalent data set name) is not set up correctly
- Dump incident is not in the directory

- Incident could have been previously deleted from the directory.

System action: The requested CIM operation is returned in error. If the failure occurred while performing a set tracking number or set PMR number operation, the function ends without having updated either value.

System programmer response: Verify that the sysplex dump directory exists and is usable. Default name is SYS1.DDIR. For more information, see the topic on troubleshooting problems in *z/OS Management Facility User's Guide*. If the problem persists, contact IBM Service for assistance.

User response: Report this problem to your system programmer.

CEZ05005E System REXX not available.

Explanation: A CIM method was invoked, requiring the invocation of a system REXX exec. However, the System REXX address space (AXR) or facilities that it provides are not available.

System action: The requested CIM operation is returned in error.

System programmer response: Enter the command START AXRPSTRT from the operator console to start System REXX. Verify that System REXX is active with the D A,AXR command.

User response: Report this problem to your system programmer.

CEZ05006E System REXX is not configured to support compiled REXX execs.

Explanation: A CIM method was invoked, requiring the invocation of a system REXX exec. However, the System REXX component cannot process the exec. This usually indicates that the run time support for compiled REXX has not been set up.

System action: The requested CIM operation is returned in error.

System programmer response: The REXX library and the REXX Alternate library must be installed. Refer to the Program Directory of these optional products for installation instructions.

User response: Report this problem to your system programmer.

CEZ05007W The request *method-name* has timed out.

Explanation: A CIM method was invoked, requiring the invocation of a system REXX exec that timed out.

System action: The requested CIM operation is returned in error.

System programmer response: This is an internal

problem related to the TIMEINT parameter on the AXREXX macro. Contact IBM Service for assistance.

User response: Report this problem to your system programmer.

CEZ05008W The request *method-name* could not be processed at this time.

Explanation: A CIM method was invoked, but System REXX is overloaded and cannot schedule the corresponding REXX exec to run at this time.

System action: System REXX limits the number of active and waiting requests to 5000. The requested CIM operation is returned in error.

System programmer response: Enter the command SYSREXX STATUS and check the value specified as "REQUESTS QUEUED" in message AXR0200I. Have the user retry the operation when there are fewer System REXX requests being processed. If still unsuccessful, contact IBM Service for assistance.

User response: Report this problem to your system programmer.

CEZ05009E SYS1.MIGLIB is not APF authorized.

Explanation: A CIM method was invoked that requires the use of an authorized service in SYS1.MIGLIB (such as AMATERSE). However, SYS1.MIGLIB is not APF authorized, which prevents CEA from invoking those programs.

System action: The requested CIM operation is returned in error.

System programmer response: From the operator console, enter the command
SETPROG APF,ADD,DSN=SYS1.MIGLIB,
VOL=<volser>

where <volser> is the volume on which MIGLIB resides.

User response: Report this problem to your system programmer.

CEZ05010E User *user-name* not authorized to view operator log snapshot *logstream-or-dataset-name*.

Explanation: A CIM method was invoked, referencing an OPERLOG snapshot for a specific incident, but the invoker is not SAF authorized to view information about the snapshot. OPERLOG diagnostic snapshots are stored in DASD log streams with data set names containing the high level data set qualifier specified in the CEAPRMxx PARMLIB member.

System action: The requested CIM operation is returned in error.

System programmer response:

- The security administrator must authorize the invoker of the service to the high-level qualifier (HLQ) of this dataset.
- The PARMLIB member CEAPRM00 (or the customized member CEAPRMxx, where xx is the suffix particular to your system) should contain the customized HLQ value or its default ('CEA').

User response: Report this problem to your system programmer.

CEZ05011E The System Logger is not available. CEAERRO_Diag4=*code*

Explanation: A CIM method was invoked, attempting to access a DASD log stream, but the System Logger facility is not available. The *code* value associated with CEAERRO_Diag4 refers to a system logger return code.

System action: The requested CIM operation is returned in error.

System programmer response:

- See the description of IXGCON in *z/OS MVS Data Areas, Vol 3* for an explanation of the logger reason code in CEAERRO_Diag4.
- If the system is not running with a logger couple data set, this is a permanent condition for the IPL. Otherwise, restart the system logger and enter the request again.

User response: Report this problem to your system programmer.

CEZ05012E The Common Event Adapter (CEA) event *event-name* was forced removed by the system operator.

Explanation: The system operator used the CEAunsubscribe console command to force the removal of this event while there was a CIM user subscribed to it. The following console command may have been issued:

```
f cea,diag,remove,client=clientname,  
event=eventname
```

System action: The CIM indication will no longer be surfaced.

System programmer response: Avoid removing events that have outstanding subscriptions.

User response: Unsubscribe to the event specified in the message and resubscribe.

CEZ05013E Common Event Adapter (CEA) is running in minimum mode.

Explanation: The system operator has forced CEA into 'minimum mode' by using the command:

```
f cea,mode=min
```

CIM indication processing is unavailable.

System action: CIM indications will not be supported.

System programmer response: Change CEA to run in 'full mode'. The following console command can be used:

```
f cea,mode=full
```

User response: Contact your system programmer.

CEZ05014E Internal error detected in provider module *module-name* while invoking method *method-name*.

Explanation: A CIM method was invoked, but an internal provider error occurred in the CIM provider.

System action: The requested CIM operation is returned in error.

System programmer response: Contact IBM Service for assistance.

User response: Report this problem to your system programmer.

CEZ05015E Target operating system *version/release* not supported for provider module *module-name* method *method-name*.

Explanation: A CIM method was invoked, but the provider requires the identified minimum operating system *version/release*.

System action: The requested CIM operation is returned in error.

System programmer response: Contact IBM Service for assistance.

User response: Report this problem to your system programmer.

CEZ05016E IPCS Sysplex Dump Directory failure.

Explanation: A CIM method was invoked to locate incident information, but the Common Event Adapter (CEA) component encountered a File Open Error when accessing the sysplex dump directory (SYS1.DDIR or equivalent data set name). A possible cause is that SYS1.DDIR is not set up correctly.

System action: The requested CIM operation is returned in error. If the failure occurred while performing a set problem tracking number or set PMR

number operation, the function will end without having updated the value.

System programmer response:

- Verify that the sysplex dump directory exists and is usable. Default name is SYS1.DDIR.
- For more information, see the topic on troubleshooting problems in *IBM z/OS Management Facility User's Guide*.
- If you still encounter a problem, contact IBM Service for assistance.

User response: Report this problem to your system programmer.

CEZ05017E IPCS Sysplex Dump Directory busy. Please try request again.

Explanation: A CIM method was invoked to locate incident information, but the Common Event Adapter (CEA) experienced an ENQ Problem when accessing the Sysplex Dump Directory (SYS1.DDIR). A possible cause is that a job or IPCS user is accessing SYS1.DDIR while CEA is attempting to access it.

System action: The requested CIM operation is returned in error.

System programmer response: Ensure that no other users are attempting to access the sysplex dump directory at the same time by checking for an exclusive ENQ on SYS1.DDIR (using D GRS). If so, consider cancelling the suspect user or job.

User response: Report this problem to your system programmer.

CEZ10000E Unable to obtain a passticket for GPMSERVE. RACF permissions probably missing

Explanation: The Monitoring providers were unable to obtain a valid passticket for the application GPMSERVE (RMF Distributed Data Server).

System action: The CIM request is not processed.

System programmer response: Make sure that the RMF Distributed Data Server is set up for accepting PassTickets as described in *z/OS RMF User's Guide*.

User response: Contact your system programmer.

CFZ-prefix messages

| **CFZ00409E Bind failed: *subsequent message*.**

| **Explanation:** The CIM server is unable to bind the socket.

| **System action:** None.

| **System programmer response:** The reason for the bind failure is described in the *subsequent message*.

| **User response:** Report this problem to your system programmer.

CFZ02202W Property value is not valid: *name=value*

Explanation: The value that was specified for the configuration property is not valid. See Chapter 9, "CIM server configuration," on page 53 for the correct

values of configuration properties.

System action: None.

System programmer response: None.

User response: Re-enter the command specifying a correct value for the configuration property.

CFZ02207W The configuration property *name* is not dynamic.

Explanation: The configuration property *name* cannot be changed dynamically for a running CIM server. Instead the change has to be made as a planned value to become effective after a CIM server restart. See “cimconfig” on page 79 or “MODIFY console command” on page 113 for details on how to change planned values.

System action: None.

System programmer response: None.

User response: Change the planned configuration value and restart the CIM server.

CFZ02300I Configuration property *conf-property* is not supported. Setting ignored.

Explanation: The mentioned configuration property is no longer supported.

System action: The CIM server ignores this setting and continues.

System programmer response: Please remove the mentioned configuration property from the planned configuration of the CIM server's */etc/wbem/cimserver_planned.conf*.

User response: None.

CFZ03029E Unsupported *UserContext* value: “*value*”.

Explanation: A provider module was registered with a *UserContext* value of *value*, but that value is not supported by this version of the CIM server. Valid values are 2 for “Requestor” and 3 for “Designated User”.

System action: The provider module is not registered.

System programmer response: Check the provider registration MOF and replace the invalid *UserContext* value with a value that is valid on z/OS.

User response: Contact your system programmer.

CFZ03030E Missing *DesignatedUserContext* property in PG_ProviderModule instance.

Explanation: A provider module was registered with a *UserContext* value of 3 (“Designated User”). The user ID of the designated user has to be specified in *DesignatedUserContext*, but no value was found (see

“PG_ProviderModule” on page 281).

System action: The provider module is not registered.

System programmer response: Check the provider registration MOF and add a valid user ID for the *DesignatedUserContext* property to all provider modules that are registered with a *UserContext* value of 3.

User response: Contact your system programmer.

CFZ05000E A system error occurred. Retry the CIM operation at a later time.

Explanation: A CIM-XML operation exceeds the server's memory.

System action: Stop the CIM-XML operation.

System programmer response: Look for message CFZ08101E identifying the source of the CIM-XML request. Contact the owner of the application issuing the request and analyze the reason for the size of the operation. Limit the result objects for this request. Restart the server to clean it up.

User response: Contact your system programmer.

CFZ05203W The user *user-ID* is not authorized to run operation in the namespace *namespace*.

Explanation: The user ID that invoked CIM operation *operation* is not authorized to run this operation in namespace *namespace* of the CIM server.

System action: The CIM request is denied.

System programmer response: Check the system console for further detailed error messages that indicate which authorization is missing for user *user-ID*. In most cases, the user has no UPDATE authority for profile CIMSERV in class WBEM.

User response: Contact your system administrator for obtaining the required level of authorization.

CFZ06201W Command not recognized by CIM server.

Explanation: The command that was entered in the system console is not supported by the CIM server.

System action: None.

System programmer response: None.

User response: None.

CFZ06202I STOP command received from z/OS console, initiating shutdown.

Explanation: The CIM server received the STOP command from the console.

System action: The CIM server is shutting down.

System programmer response: None.

User response: None.

CFZ06203E CIM server Console command thread cannot be created: *error-text* (errno *error-number*, reason code *X'reason-code'*).

Explanation: The CIM server cannot start the thread handling commands issued at the console. For a description of error *error-text* with error number *error-number* and the last four digits of the reason code *X'reason-code'*, see *z/OS UNIX System Services Messages and Codes*, or enter the reason code in the BPXMTEXT TSO command.

System action: None.

System programmer response: The CIM server cannot be stopped using the console command. To stop the CIM server, purge the address space or use a privileged UNIX user ID to issue the command `cimserver -s` from the UNIX System Services command prompt.

User response: Contact your system programmer.

CFZ06204E Console Communication Service failed: *error-text* (errno *error-number*, reason code *X'reason-code'*).

Explanation: The CIM server is connected to the system console by using the Console Communication Service. The CIM server received the unrecoverable error *error-text*. For a description of error *error-text* with errno *error-number* and the last four digits of the reason code *X'reason-code'*, see *z/OS UNIX System Services Messages and Codes*, or enter the reason code in the BPXMTEXT TSO command.

System action: CIM server shuts down.

System programmer response: Errno *error-number* and the last four digits of the reason code *X'reason-code'* point out the reason for the error. Check the console for more messages indicating the problem.

User response: None.

CFZ06205E CIM MODIFY command rejected due to syntax error.

Explanation: A MODIFY command was entered for the CIM server that could not be recognized due to invalid syntax.

System action: None.

System programmer response: None.

User response: Enter the command with the correct syntax.

CFZ06206I Syntax is: MODIFY
CFZCIM,APPL=CONFIG,
*name=value*æ,PLANNED]

Explanation: This messages describes the expected format for CIM server MODIFY command.

System action: None.

System programmer response: None.

User response: None.

CFZ06207E Failed to update configuration value.

Explanation: The CIM server failed to update a configuration value that was entered through the system console.

System action: None.

System programmer response: Look for other messages indicating the problem.

User response: Look for other messages indicating the problem.

CFZ06208I Updated current value for *name* to *value*.

Explanation: A configuration value for a running CIM server has immediately been updated. The changed value will stay in effect as long as the CIM server is running. After a restart the value is reset to either the default or to the planned configuration value.

System action: The change requested by the MODIFY command is now in effect.

System programmer response: None.

User response: None.

CFZ06209I Updated planned value for *name* to *value*.

Explanation: A configuration value has been updated for the planned configuration of the CIM server. It will become active after the CIM server is restarted. This change is persistent until the planned value is changed again.

System action: The change requested by the MODIFY command becomes effective after the next CIM server restart.

System programmer response: None.

User response: None.

CFZ06210I This change will become effective after CIM server restart.

Explanation: The change requested by the MODIFY command will not be in effect until the CIM server is restarted.

System action: None.

System programmer response: None.

User response: None.

CFZ06211E MODIFY command failed: *message*

Explanation: A configuration update requested through the MODIFY command failed. The detailed cause is indicated by *message*.

System action: None.

System programmer response: None.

User response: None.

CFZ06212E *name* is not a valid configuration property.

Explanation: The configuration property *name* is not recognized by the CIM server as a valid configuration property.

System action: None.

System programmer response: None.

| **User response:** Use the correct name for the
| configuration property and enter the command again.

| **CFZ07801E CIM HTTP or HTTPS connection failed
| to create the socket.**

| **Explanation:** The CIM server was unable to create a
| socket.

| **System action:** None.

| **System programmer response:** Check the PORT and
| PORTRANGE statements in the PROFILE.TCPIP
| configuration file to ensure that the ports specified by
| the *httpPort* and *httpsPort* CIM server configuration
| properties are accessible by the CIM server. Check the
| security product configuration to ensure that the CIM
| server is able to access the ports specified by the
| *httpPort* and *httpsPort* CIM server configuration
| properties.

| For example, OEM security product ACF2 may require
| "Stack & Port security authorization" for the CIM
| server. Use the TCP/IP NETSTAT ALLCONN PORT
| command to check for servers using the ports specified
| by the *httpPort* and *httpsPort* CIM server configuration
| properties.

| Example:

| TSO NETSTAT ALLCONN (PORT 5988

| **User response:** Report this problem to your system
| programmer.

**CFZ07805E Failed to bind socket on port
port-number: *error-text* (error code
error-code, reason code 0x*reason-code*).**

Explanation: Before listening on network port *port-number* the CIM server failed to bind the socket with *error-code* and 0x*reason-code*. It therefore will not be able to communicate over this network port. Probably the port is already in use by another program or has been reserved by the TCP/IP configuration.

System action: The CIM server does not start.

System programmer response: Error code *error-code* and the last four digits of the reason code 0x*reason-code* point out the reason for the error.

For a description of error *error-text* with error code *error-code* and the last four digits of the reason code 0x*reason-code*, see z/OS UNIX System Services Messages and Codes, or enter the reason code in the BPXMTEXT TSO command.

User response: None.

**CFZ07806E Failed to set permission on local domain
socket *socket*: *error-text* (error code
error-code, reason code 0x*reason-code*).**

Explanation: The CIM server is not able to set the permission on socket file *socket* for local communication.

System action: The CIM server does not start.

System programmer response: Error code *error-code* and the last four digits of the reason code 0x*reason-code* point out the reason for the error. For a description of error *error-text* with error code *error-code* and the last four digits of the reason code 0x*reason-code*, see z/OS UNIX System Services Messages and Codes, or enter the reason code in the BPXMTEXT TSO command.

User response: None.

**CFZ07807E Failed to listen on socket *socket-number*:
error-text (error code *error-code*, reason
code 0x*reason-code*).**

Explanation: The CIM server failed to listen on socket *socket-number*. It therefore will not be able to communicate over this network port. Probably the port is already in use by another program or has been reserved by the TCP/IP configuration.

System action: The CIM server does not start.

System programmer response: Error code *error-code* and the last four digits of the reason code 0x*reason-code* point out the reason for the error. For a description of error *error-text* with error code *error-code* and the last four digits of the reason code 0x*reason-code*, see z/OS UNIX System Services Messages and Codes, or enter the reason code in the BPXMTEXT TSO command.

User response: None.

CFZ08001W CIM HTTP or HTTPS connector cannot connect to *host:port*. Connection failed.

Explanation: The CIM server or a CIM client could not connect to a CIM indication listener or CIM server on *host:port*.

System action: None.

System programmer response: None.

User response: Check that the target of the connection is a valid hostname, IP connectivity exists to that host and that a CIM indication listener or a CIM server is listening on *port* of the target system.

CFZ08101E Internal server error. Connection with IP address *IP-address* closed.

Explanation: An unrecoverable error occurred during the communication with the client connected by *IP-address*.

System action: The connection is closed.

System programmer response: This message provides the affected IP address. Look for a previous CFZ message describing details of the internal error.

User response: Contact your system programmer.

CFZ09100I TCP/IP temporary unavailable.

Explanation: The TCP/IP stack used by the CIM server is not available.

System action: The CIM server is waiting for a restart of the TCP/IP stack. The CIM server will be not able to handle any commands and requests until the restart of the TCP/IP stack has completed. Currently processed requests are terminated.

System programmer response: Restart the TCP/IP stack the CIM server was using. If this stack is no longer used, restart the CIM server.

User response: None.

CFZ10024I Unable to start the CIM server. CIM server is already running.

Explanation: The CIM server detects that another instance of the CIM server is already running. There can be only one running CIM server.

System action: None.

System programmer response: Do not start the CIM server again. If you want to start a new CIM server on the system, use the stop command at the system console (/p cfzcim) or look for the CIM server running in the UNIX System Services (/d omvs,a=all) and cancel the process (/c cfzcim).

User response: None.

CFZ10025I The CIM server is listening on HTTP port *port-number*.

Explanation: The CIM server is starting up and will listen on port *port-number* for incoming requests from clients. For information about how to configure the CIM server's HTTP connections see Chapter 9, "CIM server configuration," on page 53.

System action: None.

System programmer response: None.

User response: None.

CFZ10026I The CIM server is listening on HTTPS port *port-number*.

Explanation: The CIM server is starting up and will listen on port *port-number* for incoming requests from clients using SSL encryption. Please note that special TCP/IP configuration settings are required for enabling the CIM server to support SSL encryption for HTTPS. For information about how to configure the CIM server's HTTPS connections see "Configuring the CIM server HTTPS connection using AT-TLS" on page 29.

System action: None.

System programmer response: None.

User response: None.

CFZ10028I The CIM server is listening on the local connection socket.

Explanation: The CIM server is starting up and will listen for incoming requests from clients. For information about how to configure the CIM server's HTTP connections see Chapter 9, "CIM server configuration," on page 53.

System action: None.

System programmer response: None.

User response: None.

CFZ10030I Started CIM server version *version*.

Explanation: The CIM server is now started and accepts CIM client requests.

System action: None.

System programmer response: None.

User response: None.

CFZ10031I CIM server - stopped.

Explanation: The CIM server is now stopped. CIM client requests are no longer accepted.

System action: None.

System programmer response: None.

User response: None.

| **CFZ10033E The CIM server is not started: subsequent**
| **message.**

| **Explanation:** The CIM server was not started due to
| an error condition described in *subsequent message*.

| **System action:** The CIM server is not started.

| **System programmer response:** See the error condition
| as described in the *subsequent message*.

| **User response:** Report this problem to your system
| programmer.

| **CFZ10034E CIM server repository contains files**
| **with wrong tags. Unable to set file tags.**
| **Stopping CIM server startup.**

| **Explanation:** The CIM server repository contains files
| tagged with the wrong CCSID. The CIM server tried to
| set the right CCSID (ISO8859-1) tag on this file, but was
| not successful.

| **System action:** The CIM server stops.

| **System programmer response:** Look for previously
| issued messages (CFZ10035E or equivalent LE
| messages) about access violations for path */var/wbem*.
| Grant the denied access right to the user ID running
| the CIM server. Restart the CIM server.

| **User response:** None.

| **CFZ10035E Failed to change file tag for file-name.**
| **Error (error-number): error-message.**

| **Explanation:** The CIM server is not able to change the
| file tag for the file *file-name*. For the reason, see the
| system error number *error-number* and the system error
| message *error-message*.

| **System action:** The CIM server stops.

| **System programmer response:** Correct the reason for
| failing to change the file tag. The reason is indicated by
| the system error number *error-number* and the system
| error message *error-message*.

| **User response:** None.

CFZ10036W CIM server repaired file tags for number repository files.

Explanation: The CIM server was able to restore the correct CCSID (ISO8859-1) file tag for a number of *number* repository files.

System action: None.

System programmer response: Repository file tags were missing or wrong. Please revise procedures handling files located in */var/wbem* to preserve file tags. If file tags are preserved, this message will not be displayed again.

User response: None.

| **CFZ10037E Failed to open repository directory**
| **repositoy-directory: error-text (error code**
| **error-code, reason code 0xreason-code).**

| **Explanation:** The CIM server is not able to open the
| directory *repositoy-directory* containing the repository.

| **System action:** The CIM server does not start.

| **System programmer response:** Error code *error-code*
| and the last four digits of the reason code *0xreason-code*
| point out the reason for the error. For a description of
| error *error-text* with error code *error-code* and the last
| four digits of the reason code *0xreason-code*, see *z/OS*
| *UNIX System Services Messages and Codes*, or enter the
| reason code in the BPXMTEXT TSO command.

| **User response:** None.

| **CFZ10206W No providers accepted the subscription.**

| **Explanation:** The subscription request for a CIM
| indication failed because there is no CIM indication
| provider that accepts the query contained in the
| indication filter. Either the filter contains an invalid or
| unsupported query, or an error has occurred during
| subscription processing.

| **System action:** The indication subscription fails and
| the subscription is not persistent on the CIM server.

| **System programmer response:** Check the *z/OS*
| console for other error messages that indicate the cause
| of the subscription failure.

| **User response:** Check the query in the indication filter
| and make sure this query is supported by the target
| CIM server. If the problem persists contact the system
| programmer of the target system.

| **CFZ10215W Subscription (name) in namespace**
| **namespace has no provider.**

| **Explanation:** During startup the CIM server has failed
| to re-establish a persistent CIM indication subscription
| because there is no CIM indication provider that
| accepts the query contained in the indication filter.
| Either the filter contains an invalid or unsupported

| query, or an error has occurred during subscription processing.

| **System action:** The subscription *name* is inactive.

| **System programmer response:** Check the z/OS console for other error messages that indicate the cause of the subscription failure. Correct the error(s) and then restart the CIM server.

| **User response:** None.

| **CFZ10405W Failed to deliver an indication:**
| *message-details*

| **Explanation:** The CIM server was unable to deliver a CIM indication to a subscribed indication listener. See *message-details* for the potential cause.

| **System action:** The CIM indication is not delivered and discarded.

| **System programmer response:** Ensure the destination system of the indication subscription is available and reachable. To remove obsolete indication subscriptions use the cimsub command (see “cimsub” on page 110).

| **User response:** None.

CFZ12500E Not loading dynamic load library
library-name **due to missing program control flag.**

Explanation: The CIM server runs on a system with Enhanced Security and thus does not load dynamic libraries which are not audited by a system programmer.

System action: The system does not load the named dynamic library.

System programmer response: Set the program control flag on the dynamic library using the UNIX System Services command extattr +p <filename>.

User response: Contact a system programmer to audit the dynamic library and set the program control flag.

CFZ12501E Security profile CIMSERV in CLASS WBEM must be defined. Ending CIM server.

Explanation: The CIM server detected an incomplete security setup.

System action: The CIM server does not start.

System programmer response: Complete the security setup by defining the profile CIMSERV in class WBEM. Refer to Chapter 6, “CIM server security setup,” on page 23 for further details.

User response: Contact your system programmer.

CFZ12502E CIM server user ID requires either READ access to BPX.SERVER or must be UID 0. Ending CIM server.

Explanation: The CIM server user ID must have READ access to the security profile BPX.SERVER, or, if BPX.SERVER is not defined on your system, must be a privileged user.

System action: The CIM server stops.

System programmer response: Permit the user ID to run the CIM server by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: Contact your system programmer.

CFZ12503E CIM server address space dirty due to loading from a not program controlled load library. Ending CIM server.

Explanation: The CIM server loaded a dynamic library that is not program controlled. Either the security setup is not complete or a dynamic library has been changed without a system programmer's audit.

System action: The CIM server stops.

Programmer response: Check all dynamic libraries for their program control flag and ensure that no library changed. Make sure that the Language Environment® libraries SCEERUN and SCEERUN2 are program controlled.

User response: Contact your system programmer.

CFZ12504E CIM server does not have appropriate privileges to check SAF security environment. Ending CIM server.

Explanation: The CIM server user ID must have READ access to the security profile BPX.SERVER, or, if BPX.SERVER is not defined on your system, must be privileged.

System action: The CIM server stops.

System programmer response: Permit the user ID to run the CIM server by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: Contact your system programmer.

CFZ12505E CIM server user ID requires either READ access to BPX.SERVER or must be UID 0. Ending CIM server.

Explanation: The CIM server user ID must have READ access to the security profile BPX.SERVER, or, if BPX.SERVER is not defined on your system, must be privileged.

System action: The CIM server stops.

System programmer response: Permit the user ID to run the CIM server by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: Contact your system programmer.

CFZ12506E CIM server address space dirty due loading from a not program controlled load library. Ending CIM server.

Explanation: The CIM server has loaded a dynamic library that is not program controlled. Either the security setup is not complete or a dynamic library has been changed without a system programmer's audit.

System action: The CIM server stops.

Programmer response: Check all dynamic libraries for their program control flag and ensure that no library has changed. Make sure the Language Environment libraries SCEERUN and SCEERUN2 are program controlled.

User response: Contact your system programmer.

CFZ12507W CIM server does not have surrogate for client user ID *user-ID*.

Explanation: A request sent from the user ID could not be processed. The CIM server does not have access to act as surrogate for the requesting user ID.

System action: The user request is ignored and an error message is sent to the client.

System programmer response: To permit the CIM server user ID to act as a surrogate for the client user, grant the user ID running the CIM server READ access to the RACF profile BPX.SRV.*user-ID* as described in "Switching identity (surrogate)" on page 29.

User response: Contact your system programmer.

CFZ12508W Failure *error-number* deleting thread security.

Explanation: The CIM server was not able to delete the thread level security built for a specific request.

System action: None.

System programmer response: None.

User response: None.

CFZ12509E The CIM server user ID requires either READ access to BPX.SERVER or must be UID 0. Stopping CIM server startup.

Explanation: The user ID that starts the CIM server must have READ access to the security profile BPX.SERVER, or, if BPX.SERVER is not defined on your system, must be a privileged user.

System action: The CIM server does not start.

System programmer response: Permit the user ID to run the CIM server by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: Contact your system programmer.

CFZ12510E CIM server address space dirty due to loading from a not program controlled load library. Stopping CIM server startup.

Explanation: The CIM server loaded a dynamic library that is not program controlled during startup. Probably the security setup is not complete or a dynamic library has been changed without a system programmer's audit.

System action: The CIM server does not start.

Programmer response: Check all dynamic libraries for their program control flag and ensure that no library changed. Make sure the Language Environment libraries SCEERUN and SCEERUN2 are program controlled.

User response: Contact your system programmer.

CFZ12511E CIM server does not have appropriate privileges to check SAF security environment. Stopping CIM server startup.

Explanation: The user ID that starts the CIM server must have READ access to the security profile BPX.SERVER, or, if BPX.SERVER is not defined on your system, must be a privileged user.

System action: The CIM server does not start.

System programmer response: Permit the user ID to run the CIM server by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: Contact your system programmer.

CFZ12512E Security profile CIMSERV in CLASS WBEM must be defined. Stopping CIM server startup.

Explanation: The CIM server detected an incomplete security setup on startup.

System action: The CIM server does not start.

System programmer response: To complete the security setup, define the profile CIMSERV in class WBEM. Refer to Chapter 6, "CIM server security setup," on page 23 for further details.

User response: Contact your system programmer.

CFZ12513E The CIM server user ID requires CONTROL access to security profile CIMSERV in CLASS WBEM. Stopping CIM server startup.

Explanation: The CIM server user ID requires CONTROL access to security profile CIMSERV in CLASS WBEM.

System action: The CIM server does not start.

System programmer response: To permit the CIM server user ID to perform administrative CIM tasks, give it CONTROL permission to profile CIMSERV in class WBEM. Refer to Chapter 6, "CIM server security setup," on page 23 for further details.

User response: Contact your system programmer.

CFZ12514E Security profile *profile-name* in CLASS WBEM must be defined.

Explanation: A provider defined a security profile at registration that is not defined for RACF class WBEM.

System action: None.

System programmer response: Create the RACF profile in class WBEM and permit users who should have access to the provider. Verify if the security profile is defined for RACF and make sure that the class WBEM has been refreshed. Verify if the provider really should be registered with the mentioned security profile and if it should be checked.

User response: Contact your system programmer.

CFZ12515W User *user-ID* not authorized to perform intrinsic CIM operation *operation* against provider *provider-name*. *access-type* access to *profile-name* in CLASS WBEM required.

Explanation: User *user-ID* is not authorized to perform CIM operation *operation* involving the provider *provider-name*. The user needs *access-type* access to SAF security profile *profile-name* that is defined in class WBEM.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: Verify if the user should be permitted to perform the current request. If so, grant the user *access-type* access to the profile *profile-name*.

User response: None. Access has been denied to a user with insufficient authority.

CFZ12516E CIM server does not have appropriate privileges to check SAF security environment. Ending CIM server.

Explanation: The CIM server user ID must have READ access to the security profile BPX.SERVER, or, if

BPX.SERVER is not defined on your system, must be a privileged user.

System action: The CIM server stops.

System programmer response: Permit the user ID to run the CIM server by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: None.

CFZ12517E Missing IdentityContainer (no username) in request.

Explanation: The security component of the CIM server detected an invalid operation context that does not contain a username.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: None.

User response: None.

CFZ12519E An unexpected error occurs: *error-text* (error number *error-number*, reason code *0xreason-code*). Stopping CIM server startup.

Explanation: During startup, the CIM server received the unrecoverable error *error-text*. For a description of error *error-text* with error number *error-number* and the last four digits of the reason code *0xreason-code*, see *z/OS UNIX System Services Messages and Codes*, or enter the reason code in the BPXMTEXT TSO command.

System action: The CIM server does not start.

System programmer response: Error number *error-number* and the last four digits of the reason code *0xreason-code* point out the reason for the error. Check the console for more messages indicating the problem.

User response: Contact your system programmer.

CFZ12520E CIM server did not set *Must Stay Clean*. Stopping provider agent startup.

Explanation: The provider agent determined that the *Must Stay Clean* flag was not set. The provider agent startup is not processed by the CIM server.

System action: The provider agent does not start.

System programmer response: Ensure that the provider agent can only be started by the CIM server.

User response: Contact your system programmer.

CFZ12521E An unexpected error occurs: *error-text* (error number *error-number*, reason code *X'reason-code'*). Stopping provider agent startup.

Explanation: During startup, the provider agent received the unrecoverable error *error-text*. For a description of error *error-text* with error number *error-number* and the last four digits of the reason code *X'reason-code'*, see *z/OS UNIX System Services Messages and Codes*, or enter the reason code in the BPXMTEXT TSO command.

System action: The provider agent does not start.

System programmer response: Error number *error-number* and the last four digits of the reason code *X'reason-code'* point out the reason for the error. Check the console for more messages indicating the problem.

User response: Contact your system programmer.

CFZ12523E CIM Runtime Environment user ID requires either READ access to BPX.SERVER or has to be UID 0. Stopping provider agent startup.

Explanation: The user ID that runs the provider agent must have READ access to the security profile BPX.SERVER, or, if BPX.SERVER is not defined on your system, must be a privileged user.

System action: The provider agent does not start.

System programmer response: Permit the user ID to run the CIM server by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: Contact your system programmer.

CFZ12524E Provider agent address space dirty due to loading from a not program controlled load library. Stopping provider agent startup.

Explanation: The provider agent has loaded a dynamic library that is not program controlled. Either the security setup is not complete or a dynamic library has been changed without a system programmer's audit.

System action: The provider agent does not start.

System programmer response: Check all dynamic libraries for their program control flag and ensure that no library has changed. For details on program control look at *z/OS UNIX System Services Planning* and *z/OS Security Server RACF Security Administrator's Guide*.

User response: Contact your system programmer.

CFZ12525E CIM Runtime Environment does not have appropriate privileges to check SAF security environment. Stopping provider agent startup.

Explanation: The user ID that runs the provider agent must have READ access to the security profile BPX.SERVER, or, if BPX.SERVER is not defined on your system, must be a privileged user.

System action: The provider agent does not start.

System programmer response: Permit the user ID to run the provider agent by either giving it READ access to profile BPX.SERVER, or, if not running in an Enhanced Security environment, set the UID to 0.

User response: Contact your system programmer.

CFZ12526E Unsupported *UserContext* value: "*value*".

Explanation: A provider module was registered with a *UserContext* value of *value*, but that value is not supported by this version of the CIM server. Valid values are 2 ("Requestor") and 3 ("Designated User").

System action: The addressed provider module is not correctly registered. The request fails and an error is sent back to the requestor.

System programmer response: Identify the failing provider module, remove the provider using the *cimprovider* utility (see "cimprovider" on page 81) and re-register the provider with a correct provider registration MOF.

User response: Contact your system programmer.

CFZ12527E Missing *DesignatedUserContext* property in PG_ProviderModule instance.

Explanation: A provider module was registered with a *UserContext* value of 3 ("Designated User"). The user ID of the designated user has to be specified in *DesignatedUserContext*, but no value was found (see "PG_ProviderModule" on page 281).

System action: The request that is directed against the provider module in error will fail and an error is sent back to the requestor.

System programmer response: Identify the failing provider module, remove the provider using the *cimprovider* utility (see "cimprovider" on page 81) and re-register the provider with a correct provider registration MOF.

User response: Contact your system programmer.

CFZ12528I Cannot switch to designated user *user-ID*. User is unknown to the security product, or has no OMVS segment.

Explanation: The CIM server failed to switch the security context to *user-ID* for a provider configured

with a designated user context. The user *user-ID* defined for the provider's security context is not defined to the system or does not have an OMVS segment.

System action: The request fails and an authorization error is sent back to the requestor/client.

System programmer response: Check if the user *user-ID* is the right user ID to run with or check for the existence of the user *user-ID* within your security product with the appropriate OMVS segment. If the problem persists you may want to remove the failing provider using the cimprovider utility and re-register the provider with the correct designated user defined in the provider registration MOF.

User response: None.

CFZ12529E An unexpected error occurred when switching to user *user-ID*: *error-text* (error code *error-code* , reason code *0xreason-code*).

Explanation: The CIM server failed to switch to *user-ID* for the designated user context of a provider.

System action: The request fails and an authorization error is sent back to the requestor/client.

System programmer response: Error code *error-code* and the last four digits of the reason code *0xreason-code* point out the reason for the error. For a description of error *error-text* with error code *error-code* and the last four digits of the reason code *0xreason-code*, see *z/OS UNIX System Services Messages and Codes*, or enter the reason code in the BPXMTEXT TSO command.

User response: None.

CFZ12530E Cannot switch to user *user-ID* because a SAF authorization error occurred. For the reason, see the SAF RACROUTE EXTRACT service reason code *reason-code*.

Explanation: A SAF authorization error has occurred. The message returns the SAF specific reason code. For RACF, the two rightmost bytes contain the RACF return code and the RACF reason code.

Example: For reason code 0x0BE80820, the RACF return code is 08 and the RACF reason code is 20.

System action: The CIM server terminates the user request.

System programmer response: Use the reason-code for your SAF RACROUTE EXTRACT service to find more details to resolve the authorization error.

For RACF: For details of the authorization error, use the RACF return code and reason code. See the *z/OS UNIX System Services Programming: Assembler Callable Services Reference* , table "RACF return and reason

codes", for the specific reason of the failure.

User response: Report this problem to your system programmer.

CFZ12532I CIM server successfully registered to ARM using element name *CFZ_SRV_system-name*.

Explanation: The CIM server successfully registered to the Automatic Restart Manager.

System action: None.

System programmer response: None.

User response: None.

CFZ12533I CIM server failed to register with ARM using element name *CFZ_SRV_system-name*: return code *X'error-number'*, reason code *X'reason-code'*.

Explanation: The CIM server failed to register with the Automatic Restart Manager using the element name *CFZ_SRV_system-name*.

System action: None.

System programmer response: If you do not want to use the Automatic Restart Manager, you can ignore this message. If you want to use ARM, use *X'error-number'* and *X'reason-code'* to look up the return and reason codes for the IXCARM macro in the *z/OS MVS Programming: Sysplex Services Reference* for the reason to fail to register with ARM.

User response: None.

CFZ12534W Authorization failed: User ID *user-ID* does not have CONTROL permission to profile CIMSERV CL(WBEM).

Explanation: The user ID requesting an administrative task, for example, cimconfig or cimprovider, does not have the required permission.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: Permit the user to perform administrative CIM tasks by giving him CONTROL permission to profile CIMSERV in class WBEM.

User response: Contact your system programmer.

CFZ12535W Authorization error: User ID *user-ID* cannot run the requested CIM operation because it lacks UPDATE permission to profile CIMSERV CL(WBEM).

Explanation: A client with the named user ID has sent a CIM request for a CIM write operation (SetProperty, InvokeMethod, CreateInstance, ModifyInstance,

DeleteInstance) to the CIM server without having the appropriate access rights.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: None.

User response: If you need to perform CIM write operations, ask your system programmer to grant you at least UPDATE access to profile CIMSERV CL(WBEM).

CFZ12540E ATTLS reset the connection due to handshake failure. Connection closed.

Explanation: AT-TLS reset the connection with the client due to a handshake failure.

System action: The connection is closed.

System programmer response: This message documents an unsuccessful connect to AT-TLS. If this prevents a connection from a client to the server, switch on tracing at the AT-TLS policy to find the reason for this closure.

User response: Contact your system programmer.

CFZ12541E An unexpected error occurs: *error-text* (error number *error-number*, reason code *X'reason-code'*). Connection closed.

Explanation: While querying the AT-TLS connection using `ioctl()`, the CIM server received an unknown error. For a description of error *error-text* with error number *error-number* and the last four digits of the reason code *X'reason-code'*, see *z/OS UNIX System Services Messages and Codes*, or enter the reason code in the BPXMTEXT TSO command.

System action: The connection is closed.

System programmer response: Contact IBM support.

User response: Contact your system programmer.

CFZ12542E ATTLS policy is not active for the CIM server HTTPS port. Communication not secured. Connection closed.

Explanation: The CIM server is configured to use HTTPS by defining the configuration property `enableHttpsConnection`, but the AT-TLS policy is not configured correctly for the CIM server.

System action: The connection is closed.

System programmer response: Please refer to Chapter 6, "CIM server security setup," on page 23 for information about how to configure AT-TLS for the CIM server.

User response: Contact your system programmer.

CFZ12543E ATTLS policy not valid for CIM server. Set `ApplicationControlled` to OFF. Connection closed.

Explanation: The value of the property `ApplicationControlled` defined in the AT-TLS policy for the CIM server is ON. Hence, the CIM server is only aware of AT-TLS but does not control it.

System action: The connection is closed.

System programmer response: Change the property `ApplicationControlled` to OFF in the AT-TLS policy defined for the CIM server. Refer to Chapter 6, "CIM server security setup," on page 23 for information about how to configure AT-TLS for the CIM server.

User response: None.

CFZ12544E ATTLS policy specifies the wrong HandshakeRole for the CIM server HTTPS port. Communication not secured. Connection closed.

Explanation: The property `HandshakeRole` defined in the inbound AT-TLS policy for the CIM server is not configured correctly.

System action: The connection is closed.

System programmer response: Change the property `HandshakeRole` to `ServerWithClientAuth` or to the server at the inbound AT-TLS policy defined for the CIM server. Refer to Chapter 6, "CIM server security setup," on page 23 for information about how to configure AT-TLS for the CIM server.

User response: None.

CFZ12545E Automatic repository upgrade failed at step *step-number*. Stopping CIM server startup.

Explanation: The CIM server failed to automatically migrate the old repository in `/var/wbem` to the new schema level. No actual migration action was run, because the basic setup is not correct.

System action: The CIM server does not start.

System programmer response: To find out the reason for this error, check the previously issued message. Correct the basic setup and restart the CIM server.

User response: None.

CFZ12546E Automatic repository upgrade failed at step *step-number*. Recovery completed successfully. Stopping CIM server startup.

Explanation: The CIM server failed to automatically migrate the old repository in `/var/wbem` to the new schema level. Migration started and ran to a certain point. Though they failed, the accomplished migration

actions were successfully rolled back.

System action: The CIM server does not start.

System programmer response: To find out the reason for this error, check the previously issued message. Correct the setup problem and restart the CIM server.

User response: Contact your system programmer.

CFZ12547F Automatic repository upgrade failed at step *step-number*. Recovery failed, manual intervention required. Stopping CIM server startup.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. Migration started and ran into a critical break. The attempt to roll back the taken actions failed. Manual user intervention is required to roll back taken migration actions.

System action: The CIM server does not start.

System programmer response: To find out the reason for this error, check the previously issued message. fallback the taken migration actions as described in that message. Fix the setup problem and restart the CIM server.

User response: None.

CFZ12548E Failed to initiate command: *command* with error: *error-number*.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. Processing of the named command failed with error *error-number*.

System action: The CIM server will roll back already taken migration actions. The CIM server does not start.

System programmer response: Investigate why the named command cannot perform successfully. Fix the system setup and restart the CIM server.

You can find further details in STDERR and STDOUT of the job output.

User response: Contact your system programmer.

CFZ12549E Command *command* failed with status *status-code*.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. The processing of the named command failed with status *status-code*.

System action: The CIM server will roll back the already taken migration actions. CIM server does not start.

System programmer response: Investigate why the named command cannot perform successfully. Fix the

system setup and restart the CIM server.

Further details can be found in STDERR and STDOUT of the job output.

User response: Contact your system programmer.

CFZ12550E Failed to rename directory *source-directory-name* to *target-directory-name* with error: *error-number*.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. Renaming of source directory to target directory failed.

System action: The CIM server will roll back already taken migration actions. CIM server does not start.

System programmer response: Investigate the reason of the renaming failure. Possible reasons are missing file access rights, a full file system or missing access right to run a program in an extra UNIX System Services address space.

User response: Contact your system programmer.

CFZ12551E Failed to create repository status files with: *error-text*.

Explanation: The CIM server failed to write the repository status file while automatically migrating the old repository in */var/wbem* to the new schema level. The migration is nearly complete, but writing the repository status file failed. The repository status file serves to avoid repeated attempts to migrate the repository.

System action: A message is logged to the system console. The CIM server startup continues.

System programmer response: Either fix the reason for the failed write of the repository status file and stop and restart the CIM server, or copy the file supplied in */usr/lpp/wbem/* to */var/wbem*.

User response: Contact your system programmer.

CFZ12552I Starting automatic repository upgrade.

Explanation: The CIM server will start to migrate the old repository to the new schema level.

System action: The CIM server starts to migrate the repository.

System programmer response: None.

User response: None.

CFZ12554E Error during automatic repository upgrade. No reference repository found at *directory-name*.

Explanation: The CIM server could not locate the new repository at location *directory-name*. No actual migration action was run, because basic setup is not correct.

System action: The CIM server does not start.

System programmer response: Check the SMP/E installation. Directory and files should have been copied to the named location in the SMP/E APPLY step.

User response: Contact your system programmer.

CFZ12555E Rename of previous repository to *directory-name* failed.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. Even though migration successfully created the new repository, renaming the old repository for backup failed.

System action: The CIM server will remove the new repository to roll back the taken migration actions. The CIM server does not start.

System programmer response: Investigate why the CIM server was unable to rename the directory */var/wbem/repository* to the directory *directory-name*. Probable causes are insufficient disk space or missing access rights.

User response: None.

CFZ12556E Rename of new repository to *directory-name* failed.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. Even though migration successfully created the new repository and backed up the old repository, renaming the new repository to */var/wbem/repository* failed.

System action: The CIM server tries to roll back the taken migration actions and also removes the new repository and renames the backed up version to */var/wbem/repository*.

System programmer response: Investigate why the CIM server was unable to rename the directory. Probable reasons are insufficient disk space or missing access rights. If fallback actions fail (indicated by message CFZ12547E), manually remove the directory named */var/wbem/repository_new* and rename the latest backed up repository version to */var/wbem/repository*.

User response: None.

CFZ12557E Failure during automatic repository upgrade. Trying to recover.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level.

System action: The CIM server will try to roll back the taken migration actions.

System programmer response: Check former and further messages for details and possible required actions.

User response: None.

CFZ12558E Failed to remove incomplete new repository at *directory-name*.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. Removing the new, migrated repository failed.

System action: The CIM server does not start.

System programmer response: Remove the directory */var/wbem/repository_new* and its subfolders and files. Check the system log for earlier messages for details on the actual migration step that failed. Fix the situation and restart the CIM server. The most common reason for this problem is insufficient disk space at */var/wbem*.

User response: None.

CFZ12559F Failed to restore previous repository on recovery. Manual rename of *source-directory-name* back to *target-directory-name* required!

Explanation: The CIM server tried to roll back the migration actions. Renaming the backed up copy of the old repository to target directory name failed.

System action: The CIM server does not start.

System programmer response: Rename the source directory to the target directory name. Investigate the reason for the failure of the automatic repository migration by checking the system log for former error messages. Fix the system setup and restart the CIM server.

User response: Contact your system programmer.

CFZ12560E Failed to create repository status file *directory-name*. Manual intervention required!

Explanation: The CIM server failed to write the repository status file while automatically migrating the old repository in */var/wbem* to the new schema level. The migration is nearly complete, but writing the repository status file failed. The repository status file serves to avoid repeated tries to migrate the repository.

System action: A message is logged to the system console. The CIM server startup continues.

System programmer response: Either fix the reason for the failed write of the repository status file and stop and restart the CIM server, or copy the file supplied in */usr/lpp/wbem/* to */var/wbem/*.

User response: Contact your system programmer.

CFZ12561E Repository in directory *directory-name* is backlevel. Run migration job for repository upgrade.

Explanation: The CIM server failed to automatically migrate the old repository in */var/wbem* to the new schema level. No actual migration action was run, because the basic setup is not correct. The old repository found at *directory-name* is not a z/OS 1.8 level repository.

System action: The CIM server does not start.

System programmer response: Use migration job CFZRCUST to migrate the repository.

User response: Contact your system programmer.

CFZ12562I Previous repository was renamed to *directory-name* for backup and can be removed.

Explanation: The CIM server successfully migrated the old repository to the new schema level. A backup copy of the old repository is stored at *directory-name*. The copy should be backed up and then can be deleted to free up disk space.

System action: The CIM server startup continues.

System programmer response: You may want to backup the old repository, and delete the copy on hard disk.

User response: None.

CFZ12563I Automatic repository upgrade completed successfully.

Explanation: The CIM server successfully migrated the old repository to the new schema level.

System action: The CIM server startup continues.

System programmer response: None.

User response: None.

CFZ12564W Failed to obtain information about file system *path-name*. Error: *error-text*.

Explanation: The CIM server failed to determine information about the file system at *path-name*. The cause of the failure was error *error-text*.

System action: Automatic repository upgrade continues.

System programmer response: None.

User response: None.

CFZ12565W File system at *path-name* is smaller than the recommended 102400 KB (100MB).

Explanation: The file system available at *path-name* should be at least 100MB large or be able to extend to that size. The CIM server might run out of space when automatically upgrading the repository.

System action: Automatic repository upgrade continues.

System programmer response: Make sure that there is enough space for data to be stored in the file system at *path-name*. Recommended is a system specific data set with at least 100MB space mounted at */var/wbem*.

User response: None.

CFZ12566W Less free space than 61440 KB (60MB) available on file system *path-name*.

Explanation: The CIM server detected less than 60MB space available in the file system *path-name*. The CIM server might run out of space when automatically upgrading the repository.

System action: Automatic repository upgrade continues.

System programmer response: Make sure that there is enough space for data to be stored in the file system at *path-name*. Recommended is a system specific data set with at least 60MB space mounted at */var/wbem*.

User response: None.

CFZ12568E ATTLS is not active for TCP-IP stack the CIM server is using for HTTPS connections. Communication not secured. Connection closed.

Explanation: The CIM server is configured to use HTTPS by defining the configuration property *enableHttpsConnection*, but the Communication Server Policy Agent was not enabled on the stack the CIM server is using when AT-TLS policy mapping was performed for the connection.

System action: The connection is closed.

System programmer response: Ensure that Communication Server Policy Agent is configured for the TCP/IP stack the CIM server is listening. Please refer to Chapter 6, "CIM server security setup," on page 23 for information about how to configure AT-TLS for the CIM server.

User response: Contact your system programmer.

CFZ12569E There is no ATTLS policy found for the CIM server HTTPS connections. Communication not secured. Connection closed.

Explanation: The CIM server is configured to use HTTPS by defining the configuration property *enableHttpsConnection*, but the Communication Server Policy Agent did not find an AT-TLS policy for the CIM server when AT-TLS policy mapping was performed for the connection.

System action: The connection is closed.

System programmer response: Ensure that a Communication Server Policy Agent policy is defined for CIM server. Please refer to Chapter 6, "CIM server security setup," on page 23 for information about how to configure AT-TLS for the CIM server.

User response: Contact your system programmer.

CFZ12570I Created directory */var/wbem*.

Explanation: CIM server successfully created the directory */var/wbem*.

System action: None.

System programmer response: None.

User response: None.

CFZ12571E Failed to create directory */var/wbem* with error: *error-message*. Stopping CIM server startup.

Explanation: CIM server failed to create the directory */var/wbem* with error *error-message*.

System action: The CIM server does not start.

System programmer response: Check the system setup for a system-specific data set mounted at path */var/wbem* with 100Mb space. Fix the problem and restart the CIM server.

User response: Contact your system programmer.

CFZ12572W Failed to read repository status file: *error-message*.

Explanation: CIM server failed to read information from the repository status file at */var/wbem*.

System action: CIM server startup proceeds and the repository is automatically migrated to the latest level available from */usr/lpp/wbem*.

System programmer response: Check the error condition described by *error-message* and fix the indicated problem in the system setup.

User response: Contact your system programmer.

CFZ12574W File *file-name* contains quotes which should be removed. Removing quotes and stopping CIM server startup. Restart the CIM server.

Explanation: CIM server found quote characters in file *file-name*. Quotes can cause environment variable setup problems.

System action: CIM server tries to remove all quotes. The CIM server does not start.

System programmer response: None.

User response: Restart the CIM server.

CFZ12575E Failed to open *file-name* for write with error: *error-message*.

Explanation: CIM server failed to open *file-name* for writing. The reason is named in *error-message*. CIM server found quote characters in the environment variable setup file for the started task procedure. CIM server tried to open the environment variable setup file to remove all quotes.

System action: CIM server does not start.

System programmer response: Remove all quotes in file *file-name* manually or check the error condition described by *error-message* and fix the indicated problem in the system setup. Restart the CIM server.

User response: Contact your system programmer.

CFZ12576F Failed to write all data to *file-name* file.

Explanation: CIM server failed to write to *file-name* for the reason named in *error-message*. CIM server found quote characters in the environment variable setup file for the started task procedure. CIM server tried to write the environment variable setup file with all quote removed, but the file was written partially.

System action: CIM server does not start.

System programmer response: Check the error condition described by *error-message* and fix the indicated problem in the system setup. Create a new environment variables setup file *file-name* using the default shipped in */usr/lpp/wbem/install*. Restart the CIM server.

User response: Contact your system programmer.

CFZ12577I Successfully removed all quotes from *file-name*.

Explanation: CIM server removed all quote characters from file *file-name*. Quotes can cause environment variable setup problems for the started task procedure. To avoid issues caused by partially setup environment variables the CIM server is stopped and needs to be restarted.

System action: CIM server does not start.

System programmer response: Restart the CIM server.

User response: Restart the CIM server.

CFZ12578W Directory */var/wbem* does not exist. CIM server will create it.

Explanation: On CIM server startup the automated migration procedure detected that path */var/wbem* does not exist.

System action: CIM server creates the directory */var/wbem*.

System programmer response: None.

User response: None.

CFZ12579W Failed switching to zIIP mode, RC=*returncode*. CIM server running on CP.

Explanation: An error occurred when the CIM server process tried to establish eligibility for running on zIIP processors.

RC=0x00000408 and
RC=0x00000508

indicate a problem with the CIM server installation in the z/OS UNIX file system.

RC=0x00000708

indicates that CIM server library *libcfzsys.so* located in */usr/lpp/wbem/lib* is not APF authorized.

System action: The CIM server process with all its threads is executing on CP processors.

System programmer response: For RC=0x00000708, use the command
`extattr +a /usr/lpp/wbem/lib/libcfzsys.so`

to restore the extended attribute to APF authorize the library.

All other return codes indicate a general problem during program execution, please contact IBM for service.

User response: Contact your system programmer.

CFZ12580I CIM server running eligible for zIIP.

Explanation: CIM server process has successfully established eligibility for running on zIIP processors.

System action: The CIM server process with all its threads is executing on zIIP processors.

System programmer response: None.

User response: None.

CFZ13006W Request user ID *user-ID* doesn't have READ permission to profile CIMSERV CL(WBEM).

Explanation: The user ID requesting a CIM operation using a remote connection is not permitted to use the CIM server.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: Permit the user to perform CIM requests by giving the user ID READ access to profile CIMSERV CL(WBEM).

User response: Contact your system programmer to permit your user ID to perform CIM requests. Repeat your request.

CFZ13007W Request user ID *user-ID* doesn't have READ permission to profile CIMSERV CL(WBEM).

Explanation: The user ID requesting a CIM operation using a local connection is not permitted to use the CIM server.

System action: The CIM request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: Permit the user to perform CIM requests by giving the user ID READ access to profile CIMSERV CL(WBEM).

User response: Contact your system programmer to permit your user ID to perform CIM requests. Repeat your request.

CFZ13607E CIM server cannot execute out-of-process provider agent: *error-text* (error number *error-number*, reason code *X'reason-code'*).

Explanation: The CIM server failed to process the out-of-process provider agent caused by the problem *error-text*. For further details, see the description of error number *error-number* and the last four digits of the reason code *X'reason-code'* in *z/OS UNIX System Services Messages and Codes*.

System action: None.

System programmer response: Stop the CIM server. Error number *error-number* and the last four digits of the reason code *X'reason-code'* point out the reason for the error. Check the console for more messages indicating the problem.

User response: Contact your system programmer.

CFZ17200W Authentication failed for user *user-ID*.

Explanation: The authentication for user *user-ID* against the z/OS system failed. Either the user ID or password contained in a request was invalid or revoked, or the user ID has not been authorized to use CIM.

System action: The CIM request is denied.

System programmer response: None.

User response: Check that you are using a valid user ID and password and that the user ID has been authorized to use CIM. If the problem persists, contact the system programmer of the target system to check for more detailed authentication error messages on the system console.

CFZ17201W Authentication failed for user *user-ID* because *enableRemotePrivilegedUserAccess* is not set to true.

Explanation: The CIM server refused login for user *user-ID*, because *user-ID* is a superuser (UID=0), and the current CIM server configuration prohibits superuser logins (the configuration option *enableRemotePrivilegedUserAccess* is false).

System action: The CIM request is denied.

System programmer response: To allow superuser login to the CIM server set the *enableRemotePrivilegedUserAccess* configuration option to true, as described in Chapter 9, "CIM server configuration," on page 53.

User response: Either use a non-superuser user ID for login to the CIM server, or contact your system administrator to enable superuser login for the CIM server.

CFZ17202W Request user ID *user-ID* doesn't have READ permission to profile CIMSERV CL(WBEM).

Explanation: The user ID requesting a CIM operation using a remote connection is not permitted to use the CIM server.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: Permit the user to perform CIM requests by giving the user READ access to profile CIMSERV CL(WBEM).

User response: Contact your system programmer to permit your user ID to perform CIM requests and afterwards repeat your request.

CFZ17203W Request user ID *user-ID* misses password.

Explanation: A request was sent to the CIM server with user *user-ID* but no password was specified.

System action: The request is rejected as unauthorized.

System programmer response: None.

User response: Specify a password with your request.

CFZ17204I CIM server authentication is using application ID OMVSAPPL.

Explanation: The CIM server is using the application ID 'OMVSAPPL' for authentication.

System action: Application ID 'OMVSAPPL' is used for authentication.

System programmer response: If the usage of application ID 'OMVSAPPL' is intended, no action has to be taken.

Otherwise, if you want to use the application ID 'CFZAPPL',

1. Set the configuration property *enableCFZAPPLID* to true
2. Restart the CIM server

User response: None.

CFZ17205W Authentication failed for user *user-ID* from client IP address *IP-address*.

Explanation: The authentication for user *user-ID* issued by the IP address *IP-address* against the z/OS system failed. Either the user ID or password contained in a request was invalid or revoked, or the user ID has not been authorized to use CIM.

System action: The CIM request is denied.

System programmer response: None.

User response: Check that you are using a valid user ID and password and that the user ID has been authorized to use CIM. If the problem persists, contact the system programmer of the target system to check for more detailed authentication error messages on the system console.

CFZ17400W Request user ID *user-ID* does not have READ permission to profile CIMSERV CL(WBEM).

Explanation: The user ID requesting a CIM operation using a local connection is not permitted to use the CIM server.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: Permit the user to

perform CIM requests by giving the user READ access to profile CIMSERV CL(WBEM).

User response: Contact your system programmer to permit your user ID to perform CIM requests and afterwards repeat your request.

CFZ17600E Change owner action of security token file failed, which is required for local authentication.

Explanation: The CIM server cannot change the ownership of a file to the user requesting local authentication. The file is located at */tmp* and the file name matches the pattern: *cimclient_<USERID>_**. The file is only valid for a short time. The server should remove this file automatically. It can be deleted.

System action: The request is not processed and an "Access Denied" notification is sent to the client.

System programmer response: Either define CHOWN.UNRESTRICTED in RACF, or grant the CIM server runtime environment user ID READ access to the SUPERUSER.FILESYS.CHOWN resource in the UNIXPRIV RACF class. For details refer to "Configuring the CIM server's resource authorization model" on page 25.

User response: Contact your system programmer.

CFZ17805I Audit logging is enabled.

Explanation: Audit logging is enabled.

System action: The CIM server starts writing SMF 86 records. These records are only recorded if the SMF configuration contains record 86 and the security is set up accordingly. For details see "Audit logging with SMF record 86" on page 69.

System programmer response: None.

User response: None.

CFZ17806I Audit logging is disabled.

Explanation: Audit logging is disabled.

System action: The CIM server stops writing SMF 86 records.

System programmer response: None.

User response: None.

CFZ18202E CIM server registration with internal SLP failed.

Explanation: The CIM server failed to register itself as a service for the Service Location Protocol (SLP). Clients will not be able to detect the CIM server on the local networking using the SLP protocol.

System action: None.

System programmer response: Check the system log for further messages indicating CIM server configuration problems or general communication problems. This message usually indicates an issue with the CIM server setup.

User response: None.

CFZ18204I SLP registration initiated.

Explanation: The CIM server has successfully registered itself as a service for the Service Location Protocol (SLP). Clients using the SLP protocol can now detect this CIM server on the local network.

System action: None.

System programmer response: None.

User response: None.

CFZ18603E Could not get CLASSPATH from environment.

Explanation: Initialization of the Java Virtual Machine failed due to environment variable CLASSPATH not being set. The CIM client request cannot be answered as JMPI (Java Managed Provider Interface) providers do not run without a correctly set CLASSPATH.

System action: None.

System programmer response: Set the CLASSPATH as described by the provider.

User response: Contact your system programmer.

CFZ20400E A system error occurred. Retry the WS-Management operation at a later time.

Explanation: A WS-Management operation exceeds the server's memory.

System action: Stop the WS-Management operation.

System programmer response: Look for message CFZ08101E identifying the source of the WS-Management request. Contact the owner of the application issuing the request and analyze the reason for the size of the operation. Limit the result objects for this request. Restart the server to clean it up.

User response: Contact your system programmer.

IWMCP001E Internal error.

Explanation: An unspecified internal error occurred. The requested operation could not be completed.

System action: No action was performed.

System programmer response: None.

User response: No action required. The function may be successful if invoked again.

IWMCP002E Severe internal error.

Explanation: An unspecified internal error occurred. The requested operation might have been partly or completely processed.

System action: Operation was partly or fully completed.

System programmer response: None.

User response: Check the system state. If the operation was not fully completed, the function may be successful if invoked again.

IWMCP003E Memory shortage.

Explanation: Storage is not available for the requested operation. The requested operation could not be performed.

System action: No action was performed.

System programmer response: None.

User response: There is a storage shortage. The function may work successfully later on.

IWMCP004E Module IWMP2PCS missing.

Explanation: Unsupported operating system environment. The WLM CIM provider requires z/OS V1R10 or higher. It cannot be used on z/OS V1R9 or lower.

System action: No action was performed.

System programmer response: Install WLM CIM provider on z/OS V1R10 or higher.

User response: None.

IWMCP005E Invalid or missing parameter.

Explanation: One or several CIM provider method parameters are not valid.

System action: No action was performed.

System programmer response: None.

User response: Check the parameters passed to CIM provider methods.

IWMCP006E Insufficient access rights.

Explanation: The caller is not authorized to perform the requested operation. The RACF facility class is active and a profile has been defined for the MVSADMIN.WLM.POLICY RACF facility class profile to which the caller does not have sufficient read or update access.

System action: No action was performed.

System programmer response: Grant user appropriate access for RACF profile MVSADMIN.WLM.POLICY.

User response: Contact the System Programmer to get the required authorization.

Part 7. Appendixes

Appendix A. Troubleshooting

This chapter contains the following subsections:

- “Garbage on the screen”
- “Typical error scenarios”

For problem determination, you can switch on tracing and logging. For details, see

- “Tracing” on page 64
- “Logging” on page 67

You can find further helpful information in Chapter 18, “z/OS specific messages,” on page 295.

Garbage on the screen

Since the z/OS CIM server and all of its command-line utilities operate in the enhanced ASCII environment, all output is written using ASCII encoding. This can lead to garbage being displayed when watching the output from the CIM server command-line utilities, sample programs or from the CIM server itself. By default, the configuration files *cimserver.env* and *profile.add* shipped with the CIM server provide the required settings for automatic conversion to the correct encoding. For details on how to enable the automatic conversion and about Enhanced ASCII in general, refer to Using Enhanced ASCII functionality in *z/OS UNIX System Services Planning*.

One important issue is that automatic conversion so far only occurs for **UNIX System Service** applications. When the output of the CIM server or any of its clients should be consumed or displayed by applications other than **UNIX System Services** applications, the conversion must take place when the data are created. To achieve this, the output files need to be tagged as EBCDIC so that, for example, the CIM server's output is converted to EBCDIC before it is consumed by these applications.

Typical error scenarios

The following is a list of typical errors that can be observed when working with CIM:

Error:

BPXP014I ENVIRONMENT MUST REMAIN CONTROLLED FOR DAEMON (BPX.DAEMON) PROCESSING.

BPXP015I HFS PROGRAM /usr/lpp/wbem/provider/<provider_library> IS NOT MARKED PROGRAM CONTROLLED.

The provider <provider_library> is not marked program controlled.

When or where seen: Messages on the console.

Solution: Mark the dynamic load library /usr/lpp/wbem/provider/<provider_library> as program controlled by using the command `extattr +p <fully qualified dynamic load library name>`. Restart the CIM server and try again.

Error: **CIM_ERR_ACCESS_DENIED**

Access to a CIM resource was not available to the client: "Not authorized to run <name of a CIM operation> in the namespace root/PG_Internal"

When or where seen: Client application / Details in the CIM server trace log

Solution: Permit the user ID to execute a configuration command with CONTROL access to Security profile CIMSERV in class WBEM.

Error: CIM runtime environment user ID requires CONTROL access to profile CIMSERV in class WBEM.

When or where seen: The CIM server error log after CIM server fails to start

Solution: The CIM server startup fails because the CIM server user ID fails to have CONTROL access to profile CIMSERV in class WBEM. Grant the CIM server user ID CONTROL access to profile CIMSERV in class WBEM.

Error: CIM runtime environment user ID requires either READ access to BPX.SERVER or it must be user ID 0.

When or where seen: The CIM server error log after CIM server fails to start

Solution: Either permit the user ID READ access to BPX.SERVER if BPX.SERVER is set up, or run the command under a privileged user ID (UID 0).

Error: CFZ17201W: ACCESS IS NOT ENABLED FOR REMOTE USERS WITH SUPERUSER AUTHORITY.

When or where seen: On the client side.

Solution: The remote client uses a local user with UID=0. However, the CIM server is configured to reject remote access if the local user is a super-user (parameter enableRemotePrivilegedUserAccess=false). If you want to enable the local user with remote privileged access, then switch the parameter to true. Otherwise, change the local user to a non-super-user by setting the UID ≠ 0.

Error:

CFZ10033E: The CIM server is not started:

CFZ00409E: Bind failed:

CFZ07801E: CIM HTTP or HTTPS connection failed to create the socket.

When or where seen: CIM server startup console messages

Solution: The CIM server cannot start because it fails to listen on one of the ports 5988 (for http) or 5989 (for https). Either the CIM server is already running, another server is listening on one of these ports, or the ports have been blocked by the TCP/IP configuration.

The *httpPort* and *httpsPort* CIM server configuration properties define the HTTP port and HTTPS port numbers (see Chapter 9, "CIM server configuration," on page 53).

- Check the PORT and PORTRANGE statements in the PROFILE.TCPIP configuration file to ensure that the specified ports are accessible to the CIM server.
- Check the security product configuration to ensure that the CIM server is able to access the specified ports. For example, OEM security product ACF2 may require "Stack & Port security authorization" for the CIM server.

— Use the TCP/IP NETSTAT ALLCONN PORT command to check for servers using the specified ports, for example issue
TSO NETSTAT ALLCONN (PORT 5988

See “Configuring the ports for the CIM server” on page 45 for more information.

Error: HTTP Error (401 Unauthorized)

When or where seen: Client application

Solution: The user authentication failed. The client application either did not provide user ID and password on a request at all, or the supplied user ID and password are not valid for the z/OS system on which the CIM server is running.

Permit the user ID to execute a client request with at least READ access to Security profile CIMSERV in class WBEM. Check the server log for a detailed error report.

Error: ICH14080I

Warning: RACF detected a possible error in the dynamic class descriptor table, entry WBEM, error code 01. The class is available for further processing. The class name does not contain a national character nor a number. To assure IBM does not create an IBM-defined class in the future by this same name, you should choose a class name which contains at least one national character or a number.

When or where seen: RACF setup of dynamic class WBEM

Solution: Ignore the warning.

Error:

**ICH408I USER(CFZSRV)
GROUP(CFZSRVGP) NAME(#####)
CL(PROCESS)
INSUFFICIENT AUTHORITY TO NEWJOBNAME**

When or where seen: Message on the console.

Solution: Grant the CIM server user ID READ access to profile BPX.JOBNAME in class FACILITY to be allowed to set the job name of the out-of-process agent to CFZOOPA (see “Running providers in separate address spaces” on page 62).

Error: IEF450I CFZCIM - ABEND=S1C7 U0000 REASON=FFFF0006

When or where seen: Message on the console.

Solution: Look for CSV042I and ICH422I program control messages. CSV042I message points out the module to be marked as program controlled. If no CSV042I and ICH422I messages occur contact IBM Service.

Example:

CSV042I REQUESTED MODULE BLSXTID NOT ACCESSED.
THE MODULE IS NOT PROGRAM CONTROLLED
ICH422I THE ENVIRONMENT CANNOT BECOME UNCONTROLLED.
CSV028I ABEND306-42 JOBNAME=CFZCIM STEPNAME=
BPXP014I ENVIRONMENT MUST REMAIN CONTROLLED FOR
DAEMON (BPX.DAEMON) PROCESSING.
IEF450I CFZCIM - ABEND=S1C7 U0000 REASON=FFFF0006 TIME=14.16.12

Error: JGP00001W: Number of Instances Exceeded Threshold

This error message might be issued at enumeration of IBMzOS_Job instances, when the number of instances to be enumerated is greater than a configured limit. This limit has been defined to prevent the CIM server from resource exhaust.

It is recommended to change your enumeration to a subset of IBMzOS_Job.

To query the current limit of the IBMzOS_Job provider, receive the IBMzOS_JobsManagementSettings instance of the CIM server. The property *MaxInstances* contains the currently defined limit.

To change the limits, set the property *MaxInstances* to a new value by modifying the IBMzOS_JobsManagementSettings instance.

```
cimcli mi
  IBMzOS_JobsManagementSettings.InstanceID=\"IBMzOS:JobsManagementSettings\"
  MaxInstances=<new_value>
```

Client Side Error: CIM_ERR_ACCESS_DENIED

Access to a CIM resource was not available to the client: "EDC5139I
Operation not permitted."

When or where seen: Client application / Details in the CIM server trace log

Solution: Permit the CIM server runtime environment user ID as surrogate for the requesting client user ID to use the command: PERMIT
BPX.SRV.<client uid> CL(SURROGAT) ID(<CIMServer UID>) ACCESS(READ)

Client side error: HTTP Error (413 Request Entity Too Large)

There wasn't enough memory available to the client to successfully read the entire response from the server into memory.

When or where seen: Client application, like for instance cimivp.

Solution: Allow the client to use more memory. If the application runs within a JOB, increase the REGION size. If the client runs from a UNIX System Services shell, increase the ASSIZEMAX value in the OMVS segment of the user running the shell.

Appendix B. Step-by-step explanation of the CFZSEC job

This appendix provides an explanation for each single step of the CIM security setup job CFZSEC.

Please note that the CFZSEC job provides a quick security setup for CIM. Because this job provides a solution for each configuration, necessarily the job steps which do not apply to your system will fail. But this does not affect the job's functionality.

The job creates security profiles, users and groups required to run CIM and grants them the necessary permissions to system resources.

Step BASICSUP

```
/* Step BASICSUP dose set-up basic security settings.
/*      - Program control for runtime libraries.
//BASICSUP EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *

RALT PROGRAM * ADDMEM('SYS1.SCEERUN'/'*****'/NOPADCHK) +
  UACC(READ)
RALT PROGRAM * ADDMEM('SYS1.SCEERUN2'/'*****'/NOPADCHK) +
  UACC(READ)

SETOPTS WHEN(PROGRAM) REFRESH
/*
```

This sets up the basic security for the CIM server. To enable the CIM server to run in a program controlled environment, the Language Environment runtime libraries SCEERUN and SCEERUN2 must be program controlled.

Step CRUSR

Step CRUSR

```
/*
/* Step CRUSR creates default groups and users required for CIM
/* CFZSRVGP - CIM server ID's default group
/* CFZADMGP - CIM admin ID's default group
/* CFZUSRGP - CIM end-users ID's default group
/*
/* CFZSRV - CIM server UserId used by Started Task
/*
//CRUSR EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *

ADDGROUP CFZSRVGP OMVS(GID(9501))
ADDGROUP CFZADMGP OMVS(GID(9502))
ADDGROUP CFZUSRGP OMVS(GID(9503))

ADDUSER CFZSRV DFLTGRP(CFZSRVGP) OMVS(UID(0) PROGRAM('/bin/sh') +
HOME('/u/cfzsrv')) NOPASSWORD NOOIDCARD
ADDSD 'CFZSRV.**' UACC(NONE)
PERMIT 'CFZSRV.**' CLASS(DATASET) ID(CFZSRV) ACCESS(ALTER)
SETROPTS GENERIC(DATASET) REFRESH
ALTUSER CFZSRV DFLTGRP(CFZSRVGP) OMVS(UID(0) PROGRAM('/bin/sh') +
HOME('/u/cfzsrv')) NOPASSWORD NOOIDCARD NOPHRASE
/*
```

This step creates or updates the user CFZSRV for running the CIM server as a started task. By default the UID for the CIM server user is set to 0 to run the CIM server with superuser privileges. While this may be sufficient for a simple setup, if you have defined the BPX.SERVER profile in the class FACILITY, and class FACILITY is activated, it is recommended to change the UID for CFZSERV to a non null value. The default in this case is 9500.

A default data set profile is created to ensure that the CIM server user ID can access its home profile and other relevant settings.

In addition this step creates distinct groups for the CIM server user (CFZSRVGP), CIM server administrators (CFZADMGP) and end users (CFZUSRGP). To grant a user access to CIM, simply connect the user to the according group, for example with the command

```
CONNECT (username) GROUP(CFZUSRGP) AUTHORITY(USE)
```

The CFZUSRGP grants a user access to all resources that are managed through CIM. Depending on how granular you want to control users' access to CIM, you may want to create additional groups that allow access only to a subset of resources managed through CIM.

Step CRWBEM

Step CRWBEM

```
/* Step CRWBEM creates class WBEM and profile CIMSERV
//CRWBEM EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *

SETROPTS CLASSACT(CDT) RACLIST(CDT)

RDEFINE +
  CDT WBEM +
  UACC(NONE) +
  CDTINFO( CASE(UPPER) +
    MAXLENGTH(246) +
    FIRST(ALPHA) +
    OTHER(ALPHA,NUMERIC) +
    MAXLENX(246) +
    KEYQUALIFIERS(0) +
    PROFILESALLOWED(YES) +
    POSIT(200) +
    DEFAULTTRC(8) +
    DEFAULTUACC(NONE) +
    RACLIST(REQUIRED))

SETROPTS RACLIST(CDT) REFRESH

SETROPTS CLASSACT(WBEM) RACLIST(WBEM)

RDEFINE WBEM CIMSERV UACC(NONE)

SETROPTS CLASSACT(WBEM) RACLIST(WBEM)
/*
```

This step creates the RACF class and profile required to control access to the CIM server.

If the POSIT value 200 for RACF is already in use on your system, change the value defined in this step.

Step PEUSR

Step PEUSR

```
/* Step PEUSR
/*      - permits default UserID's to required resources
/*      - sets up required surrogate
/*      - permits CFZSRV to BPX.SERVER (no effect if BPX.SERVER is not
/*                               enabled on the system)
/*      - authorizes CIM server to write SMF records
/*      - authorizes CIM server to write to console
//PEUSR EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSTSPRT DD SYSOUT=*
//SYSTSIN  DD *

PERMIT CIMSERV CL(WBEM) ACCESS(CONTROL) ID(CFZSRV)
PERMIT CIMSERV CL(WBEM) ACCESS(CONTROL) ID(CFZADMGP)
PERMIT CIMSERV CL(WBEM) ACCESS(UPDATE) ID(CFZUSRGP)
SETROPTS RACLIST(WBEM) REFRESH

SETROPTS CLASSACT(SURROGAT) RACLIST(SURROGAT) GENERIC(SURROGAT)
RDEFINE SURROGAT BPX.SRV.** UACC(NONE)
PERMIT BPX.SRV.** CL(SURROGAT) ACCESS(READ) ID(CFZSRV)
SETROPTS RACLIST(SURROGAT) REFRESH

PERMIT BPX.SERVER CL(FACILITY) ACCESS(UPDATE) ID(CFZSRV)
SETROPTS RACLIST(FACILITY) REFRESH

RDEFINE FACILITY BPX.SMF UACC(NONE)
PERMIT BPX.SMF CL(FACILITY) ACCESS(READ) ID(CFZSRV)
PERMIT BPX.CONSOLE CL(FACILITY) ACCESS(READ) ID(CFZSRV)
SETROPTS RACLIST(FACILITY) REFRESH

/*
```

This step grants CIM users the necessary permissions to run, to control and to access the CIM server.

In detail it grants the following permissions:

For the CIM server user:

- CONTROL access to profile CIMSERV in class WBEM
This allows the user to start the CIM server.
- READ access to profile BPX.SRV.** in class SURROGAT
This allows the CIM server to switch a TCB into a requestor's user for running client requests under the authority of the client's user.
- UPDATE access to profile BPX.SERVER in class FACILITY
This authorizes the CIM server to validate user credentials and to verify user access to RACF profiles.
- READ access to profile BPX.SMF in class FACILITY
This allows the CIM server to write SMF records when it is configured to do so. (See "Audit logging with SMF record 86" on page 69 for details on SMF support in CIM.)
- READ access to profile BPX.CONSOLE in class FACILITY
This allows the CIM server to issue messages on the z/OS console when the BPX.CONSOLE profile is defined.

For the CIM administrator group:

- CONTROL access to profile CIMSERV in class WBEM
This allows a user to perform administrative functions.

For the CIM users group:

- UPDATE access to profile CIMSERV in class WBEM
This allows a user to access CIM as a regular user.

Step PEAPPL

Step PEAPPL

```
/* Step PEAPPL Permit CIM groups and users to net application CFZAPPL
/*          This has no effect if class APPL is not active.
//PEAPPL EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSTSIN DD *
RDEFINE APPL CFZAPPL UACC(NONE)
PERMIT CFZAPPL CL(APPL) ACCESS(READ) ID(CFZSRV)
PERMIT CFZAPPL CL(APPL) ACCESS(READ) ID(CFZADMGP)
PERMIT CFZAPPL CL(APPL) ACCESS(READ) ID(CFZUSRGP)
SETROPTS RACLIST(APPL) REFRESH
/*
```

When class APPL is active, the CFZAPPL profile protects access to the CIM server application. Any user who wants to access the CIM server requires at least READ access to the CFZAPPL profile in the APPL class. This job step grants this access for the CIM server user, the CIM administrator group, and the CIM users group.

Step SETARM

Step SETARM

```
/* Step SETARM establishes security setup required for ARM
/*          A sample ARM policy (CFZARMP) resides in the installed
/*          SYS1.SAMPLIB
//SETARM EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSTSIN DD *
SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY) GENERIC(FACILITY)
RDEFINE FACILITY IXARM.DEFAULT.CFZ_SRV * UACC(NONE)
PERMIT IXARM.DEFAULT.CFZ_SRV * CLASS(FACILITY) +
ID(CFZSRV) ACCESS(UPDATE)

SETROPTS RACLIST(FACILITY) REFRESH
/*
```

This step enables the CIM server for registering with the z/OS Automatic Restart Manager (ARM).

To completely enable the CIM server for ARM, additional customization is required as described in “Automatically restarting the CIM server” on page 70.

Step ENSTC

Step ENSTC

```
/* Step ENSTC establishes CFZSRV as the Started Task User for CIM
//ENSTC EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *
  SETROPTS CLASSACT(STARTED) RACLIST(STARTED) GENERIC(STARTED)
  RDEFINE STARTED CFZCIM.* STDATA(USER(CFZSRV) GROUP(CFZSRVGP))
  SETROPTS RACLIST(STARTED) REFRESH
/*
```

This step connects the CIM server started task procedure CFZCIM with the CIM server user CFZSRV.

For further details on configuring the CIM server started task procedure, see “Customizing the started task procedure CFZCIM” on page 49.

Step PECEA

Step PECEA

```
/* Step PECEA permits CIM Cluster and JES jobs provider to access CEA
/*
//PECEA EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSTSIN DD *
  ADDSD 'CEA.*' UACC(NONE)
  PERMIT 'CEA.*' CLASS(DATASET) ID(CFZUSRGP) ACCESS(ALTER)
  PERMIT 'CEA.*' CLASS(DATASET) ID(CFZADMGP) ACCESS(ALTER)
  SETROPTS GENERIC(DATASET) REFRESH

  SETROPTS CLASSACT(SERVAUTH) RACLIST(SERVAUTH) GENERIC(SERVAUTH)
  RDEFINE SERVAUTH CEA.* UACC(NONE)

  PERMIT CEA.* CLASS(SERVAUTH) ID(CFZADMGP) ACCESS(UPDATE)
  PERMIT CEA.* CLASS(SERVAUTH) ID(CFZUSRGP) ACCESS(UPDATE)

  PERMIT CEA.CONNECT CLASS(SERVAUTH) ID(CFZADMGP) ACCESS(UPDATE)
  PERMIT CEA.SUBSCRIBE.* CLASS(SERVAUTH) ID(CFZADMGP) ACCESS(UPDATE)
  PERMIT CEA.SUBSCRIBE.ENF_0068* CLASS(SERVAUTH) ID(CFZADMGP) +
  ACCESS(UPDATE)
  PERMIT CEA.CEAGETPS CLASS(SERVAUTH) ID(CFZADMGP) ACCESS(UPDATE)
  PERMIT CEA.CEADOCMD CLASS(SERVAUTH) ID(CFZADMGP) ACCESS(UPDATE)
  PERMIT CEA.CEAPDWB* CLASS(SERVAUTH) ID(CFZADMGP) ACCESS(UPDATE)
  PERMIT CEA.CEADOCONSOLECMD CLASS(SERVAUTH) ID(CFZADMGP) ACCESS(UPDATE)

  PERMIT CEA.CONNECT CLASS(SERVAUTH) ID(CFZUSRGP) ACCESS(UPDATE)
  PERMIT CEA.SUBSCRIBE.* CLASS(SERVAUTH) ID(CFZUSRGP) ACCESS(UPDATE)
  PERMIT CEA.SUBSCRIBE.ENF_0068* CLASS(SERVAUTH) ID(CFZUSRGP) +
  ACCESS(UPDATE)
  PERMIT CEA.CEAGETPS CLASS(SERVAUTH) ID(CFZUSRGP) ACCESS(UPDATE)
  PERMIT CEA.CEADOCMD CLASS(SERVAUTH) ID(CFZUSRGP) ACCESS(UPDATE)
  PERMIT CEA.CEAPDWB* CLASS(SERVAUTH) ID(CFZUSRGP) ACCESS(UPDATE)
  PERMIT CEA.CEADOCONSOLECMD CLASS(SERVAUTH) ID(CFZUSRGP) ACCESS(UPDATE)

  SETROPTS RACLIST(SERVAUTH) REFRESH
/*
```

This step permits CIM users and administrators to access CEA through the CIM providers for the OS management Jobs and Cluster classes described in “OS management Job classes” on page 160 and “OS management Cluster classes” on page 191.

Note: This step defines the generic resource profile CEA.* and permits the CIM default groups CFZADMGP and CFZUSRGP access to it.

For the case that you have already defined the specific resource profiles (CEA.CONNECT, etc), this step also permits the CIM default groups to these specific resource profiles.

Depending on what you have actually defined, you can customize this job step to match your environment by removing obsolete commands.

For granting users a more fine grained access to CIM you may consider to define an additional group here that grants access just for OS management Jobs and Cluster classes.

For further details on the required setup for using the OS management Jobs and Cluster classes see “Setting up the CIM server for Cluster, CoupleDataset, and JES2-JES3Jobs providers” on page 38.

Step ENCLCDS

Step ENCLCDS

```
/* Step ENCLCDS Setup for Cluster/Couple Dataset Providers
/*
//ENCLCDS EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *

SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY) GENERIC(FACILITY)

RDEFINE FACILITY MRCLASS.CLUSTER UACC(NONE)
PERMIT MRCLASS.CLUSTER CLASS(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT MRCLASS.CLUSTER CLASS(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)

RDEFINE FACILITY MVSADMIN.* UACC(NONE)
PERMIT MVSADMIN.* CLASS(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT MVSADMIN.* CLASS(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)
PERMIT MVSADMIN.XCF.* CLASS(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT MVSADMIN.XCF.* CLASS(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)
PERMIT MVSADMIN.XCF.CFRM CLASS(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT MVSADMIN.XCF.CFRM CLASS(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)

SETROPTS RACLIST(FACILITY) REFRESH
/*
```

This step permits CIM users and administrators to use the CIM providers for the OS management Cluster classes described in “OS management Cluster classes” on page 191.

For granting users a more fine-grained access to CIM, you may consider to define an additional group here that grants access just for OS management Cluster classes.

For further details on the required setup for using the OS management Cluster classes see “Setting up the CIM server for Cluster, CoupleDataset, and JES2-JES3Jobs providers” on page 38.

Step ENSMIS

Step ENSMIS

```
/* Step ENSMIS enables the SMI-S CIM providers
//ENSMIS EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSTSPRT DD SYSOUT=*
//SYSTSIN DD *
SETROPTS CLASSACT(FACILITY) RACLIST(FACILITY) GENERIC(FACILITY)
RDEFINE FACILITY IOSCDR UACC(NONE)

PERMIT IOSCDR CL(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT IOSCDR CL(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)
PERMIT IOSCDR CL(FACILITY) ID(CFZSRV) ACCESS(UPDATE)

SETROPTS CLASSACT(SERVAUTH) RACLIST(SERVAUTH) GENERIC(SERVAUTH)

RDEFINE SERVAUTH CEA.* UACC(NONE)
PERMIT CEA.* CLASS(SERVAUTH) ID(CFZSRV) ACCESS(READ)
PERMIT CEA.CONNECT CLASS(SERVAUTH) ID(CFZSRV) ACCESS(READ)
PERMIT CEA.SUBSCRIBE.ENF_0009* CLASS(SERVAUTH) ID(CFZSRV) +
ACCESS(READ)
PERMIT CEA.SUBSCRIBE.ENF_0027* CLASS(SERVAUTH) ID(CFZSRV) +
ACCESS(READ)
PERMIT CEA.SUBSCRIBE.ENF_0033* CLASS(SERVAUTH) ID(CFZSRV) +
ACCESS(READ)

SETROPTS RACLIST(FACILITY) REFRESH
SETROPTS RACLIST(SERVAUTH) REFRESH
/*
```

This step permits the CIM server user ID to access CEA through the CIM live cycle indication providers for the Storage management classes as described in “Storage management classes” on page 233.

In particular a CIM user requires this permission to access the CIM providers for the following storage management classes:

- IBMzOS_SBProtocolEndpoint
- Association IBMzOS_SBIInitiatorTargetLogicalUnitPath

This step defines the generic resource profile CEA.* and permits the default CIM server user ID CFZSRV access to it. For the case that you have already defined the specific resource profiles such as CEA.CONNECT, this step also permits the default CIM server user ID to these specific resource profiles. Depending on what you have actually defined, you can customize this job step to match your environment by removing obsolete commands.

For granting users a more fine-grained access to CIM, you may consider to define an additional group that grants access just for Storage management classes.

Step ENTICIP

Step ENTICIP

```
/* Step ENTICIP enables the Network CIM providers
//ENTICIP EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSTSIN DD *

SETOPTS CLASSACT(SERVAUTH) RACLIST(SERVAUTH) GENERIC(SERVAUTH)
RDEFINE SERVAUTH EZB.CIMPROV.* UACC(NONE)

PERMIT EZB.CIMPROV.* CL(SERVAUTH) ID(CFZADMGP) ACCESS(READ)
PERMIT EZB.CIMPROV.* CL(SERVAUTH) ID(CFZUSRGP) ACCESS(READ)

SETOPTS RACLIST(SERVAUTH) REFRESH
/*
```

This step permits CIM users and administrators to use the CIM providers for the OS management Network classes described in “OS management Network classes” on page 154.

For granting users a more fine-grained access to CIM, you may consider to define an additional group here that grants access just for the OS management Network classes.

Step ENWLM

Step ENWLM

```
/* Step ENWLM Setup for WLM Providers
/*
//ENWLM EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSTSIN DD *

SETOPTS CLASSACT(FACILITY) RACLIST(FACILITY) GENERIC(FACILITY)

RDEFINE FACILITY MVSADMIN.* UACC(NONE)
PERMIT MVSADMIN.* CLASS(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT MVSADMIN.* CLASS(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)
PERMIT MVSADMIN.WLM.* CLASS(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT MVSADMIN.WLM.* CLASS(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)
PERMIT MVSADMIN.WLM.POLICY CLASS(FACILITY) ID(CFZUSRGP) ACCESS(UPDATE)
PERMIT MVSADMIN.WLM.POLICY CLASS(FACILITY) ID(CFZADMGP) ACCESS(UPDATE)
RDEFINE PROGRAM BLSUXTID
RALT PROGRAM BLSUXTID ADDMEM('SYS1.MIGLIB'/'*****'/NOPADCHK) +
UACC(READ)

SETOPTS RACLIST(FACILITY) REFRESH
SETOPTS WHEN(PROGRAM) REFRESH
/*
```

This step permits CIM users and administrators to use the CIM providers for the WLM classes described in Chapter 15, “WLM classes,” on page 261.

For granting users a more fine-grained access to CIM, you may consider to define an additional group here that grants access just for the WLM classes.

Step ENRMF

Step ENRMF

```
/* Step ENRMF creates profiles necessary to allow passtickets being
/*          generated for authentication with the DDS
//ENRMF EXEC PGM=IKJEFT01,DYNAMNBR=99
//SYSPRINT DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSTSIN DD *
SETROPTS CLASSACT(PTKTDATA) RACLIST(PTKTDATA) GENERIC(PTKTDATA)
RDEFINE PTKTDATA GPMSEVE SSGNON(KEYMASKED(#rkeymask))
RDEFINE PTKTDATA IRRPTAUTH.GPMSEVE.* UACC(NONE)
PERMIT IRRPTAUTH.GPMSEVE.* CL(PTKTDATA) ID(CFZSRV) ACCESS(UPDATE)
SETROPTS RACLIST(PTKTDATA) REFRESH
/*
```

If you are not using the z/OS Resource Measurement Facility (RMF) optional element, remove this step from the job. Otherwise this step permits the CIM server access to the RMF Distributed Data Server using passtickets. For this, replace #rkeymask by a 16-digit (0-9,A-F) keymask value to setup connectivity between CIM and RMF via passtickets.

Note:

The keymask value is a secret passkey. In a secure environment it is recommended to execute step ENRMF separately to avoid storing the passkey in the job log in readable format.

The CIM classes implemented by RMF are described in the *z/OS RMF Programmer's Guide* and *z/OS RMF User's Guide*.

Appendix C. CEA reason codes

The following list of reason codes may be returned by the methods in the Jobs providers. The first four digits (X'xxxx') may be any value.

Table 8. Jobs providers' reason codes

Reason code (hex)	Description	User action	IBM Service Information
X'xxxx0100'	Common Event Adapter (CEA) communication unavailable.	Ensure CEA is active; Call IBM Service.	CEAUNAVAIL
X'xxxx0117'	Instrumentation is unable to accommodate additional CIM indication providers.	Remove unused/unnecessary indication provider connections from the instrumentation. Call IBM Service if this is a consistent problem.	CEAMAXCLIENTSCONNECTED
X'xxxx011F'	z/OS System Operator forced the unsubscribe of the event.	Resubscribe to the event.	CEASYSOPFORCEUNSUBSCRIBE
X'xxxx0121'	Common Event Adapter (CEA) is no longer able to communicate with CIM indication providers.	Adjust CEA by transitioning the component from minimum mode to full mode. Operator must use F CEA,MODE=FULL	CEAFORCEMINMODE
X'xxxx0126'	Instrumentation is unable to accept any more subscriptions to indication events.	Remove unused/unnecessary indication event subscriptions	CEAMAXPGMSUBSCRIBED
X'xxxx020A'	Common Event Adapter (CEA) was unable to find exit handler.	Ensure that the exit handler is installed properly by the SMP/E installation step. The handlers are usually installed in the LPA.	CEAHANDLERNOTFOUND
X'xxxx0300'	Internal CIM error.	Call IBM Service.	CEAREQUESTNOTRECOGNIZED
X'xxxx0301'	Internal CIM error.	Call IBM Service.	CEAREQUESTNOTIMPLEMENTED
X'xxxx0302'	Internal CIM error.	Call IBM Service.	CEAPROPERTYSTRUCTBADPTR
X'xxxx0303'	Internal CIM error.	Call IBM Service.	CEAPROPERTYSTRUCTBADEYE
X'xxxx0304'	Internal CIM error.	Call IBM Service.	CEAPROPERTYSTRUCTBADVERSION
X'xxxx0305'	Internal CIM error.	Call IBM Service.	CEAPROPERTYBADRESOURCE
X'xxxx0306'	Internal CIM error.	Call IBM Service.	CEAPROPERTYNOMATCH
X'xxxx0307'	Internal CIM error.	Call IBM Service.	CEAPROPERTYSTRUCTEMPTY
X'xxxx0308'	Internal CEA error.	Call IBM Service.	CEAENVBAD

Table 8. Jobs providers' reason codes (continued)

Reason code (hex)	Description	User action	IBM Service Information
X'xxxx0309'	Internal CIM error.	Call IBM Service.	CEAFILTERSTRUCTBADEYE
X'xxxx030A'	Internal CIM error.	Call IBM Service.	CEAFILTERSTRUCTBADVERSION
X'xxxx030B'	Internal CIM error.	Call IBM Service.	CEAFILTERBADRESOURCE
X'xxxx030C'	Internal CIM error.	Call IBM Service.	CEAFILTERNOMATCH
X'xxxx030D'	Internal CIM error.	Call IBM Service.	CEABADPARMPTR
X'xxxx030E'	Internal CEA error.	Call IBM Service.	CEABADSSISUBSYSTEM
X'xxxx030F'	Internal CEA error.	Call IBM Service.	CEABADSSICALL
X'xxxx0310'	Internal CEA error.	Ensure JES2/JES3 is active. Ensure that ExtendedSubsystem is available. Call IBM Service.	CEANOSSI
X'xxxx0311'	Internal CEA error.	Call IBM Service.	CEABADSSIENV
X'xxxx0312'	Internal CEA error.	Look for SDUMP. Call IBM Service.	CEAENVBADSSI
X'xxxx0314'	Internal CEA error.	Look for SDUMP. Check storage indicators (monitors). Call IBM Service if external symptom not resolved.	CEAUNABLETOALLOCATE
X'xxxx0315'	Internal CEA error.	Call IBM Service.	CEANOTJOBSTERSEELEMENT
X'xxxx0316'	Internal CEA error.	SSI Abend. Look for SDUMP. Call IBM Service.	CEAJOBCHAINBROKEN
X'xxxx0317'	Internal CEA error.	Look for SDUMP. Call IBM Service.	CEABADDATENV
X'xxxx0318'	Internal CEA error.	Look for SDUMP. Call IBM Service.	CEASYSOUTCHAINBROKEN
X'xxxx0319'	Internal CEA error.	Look for SDUMP. Call IBM Service.	CEANOTSYSOUTHRELEMENT
X'xxxx031A'	Internal CEA error.	Call IBM Service.	CEABADFREFPTR
X'xxxx031B'	Internal CEA error.	Call IBM Service.	CEABADFREFBLK
X'xxxx031C'	Internal CEA error.	Call IBM Service.	CEABADFREFENV
X'xxxx031D'	Internal CEA error.	Call IBM Service.	CEAUNABLETOFREE
X'xxxx031E'	Internal CEA error.	Call IBM Service.	CEABADIEFQRY
X'xxxx031F'	Internal CEA error.	Look for SDUMP. Call IBM Service.	CEASSCHAINBROKEN
X'xxxx0320'	Internal CEA error.	Look for SDUMP. Call IBM Service.	CEAENVBADJSQY
X'xxxx0321'	Internal CEA error.	Call IBM Service.	CEABADFILTEROPER
X'xxxx0322'	Internal CEA error.	Call IBM Service.	CEABADS54SUBSYSTEM
X'xxxx0323'	Internal CEA error.	Call IBM Service.	CEABADS54CALL
X'xxxx0324'	Internal CEA error.	SSI not activated. Call IBM Service.	CEANOS54

Table 8. Jobs providers' reason codes (continued)

Reason code (hex)	Description	User action	IBM Service Information
X'xxxx0325'	Internal CEA error.	Call IBM Service.	CEABADS54ENV
X'xxxx0327'	Internal CEA error.	Call IBM Service.	CEABADS54STOR
X'xxxx0328'	Internal CIM error.	Call IBM Service.	CEATIMEOUTMAXIMUMEXCEEDED
X'xxxx0329'	Internal CEA error.	Call IBM Service.	CEANEEDSYSOUTFILTER
X'xxxx032A'	Internal CIM error.	Call IBM Service.	CEABUFFERTOOLARGE
X'xxxx032B'	Internal CEA error.	Call IBM Service.	CEACMDSDIAGRCSET
X'xxxx032C'	Internal CEA error.	Ensure SYSREXX is active/operational using the F AXR,DISPLAY command. Call IBM Service if AXREXX is active.	CEACMDSAXREXXRCSET
X'xxxx032D'	Client not authorized for instrumentation	Ensure user has access to instrumentation facilities.	CEANOINSTRAUTH
X'xxxx032E'	Internal CIM error.	Call IBM Service.	CEATOOMUCHDATA
X'xxxx032F'	Internal CEA error.	Call IBM Service.	CEAFILTERNOTSUPPORTED
X'xxxx0330'	Internal CEA error.	Call IBM Service.	CEAPRIMARYTYPEMISMATCH
X'xxxx0331'	Internal CEA error.	Call IBM Service.	CEABADSSUBSYSTEM
X'xxxx0332'	Internal CEA error.	Call IBM Service.	CEAUNABLETOALLOCATE2
X'xxxx0333'	Internal CEA error.	Call IBM Service.	CEABADBUFFER
X'xxxx0334'	Internal CIM error.	Call IBM Service.	CEATIMEOUTLESSTHANMINIMUM
X'xxxx0335'	Internal CIM error.	Call IBM Service.	CEACMDSSYNTAXERROR
X'xxxx0336'	The CIM provider request was cancelled in-process.	Retry the command request. If it does not work, call IBM Service.	CEACMDSHALTERERROR
X'xxxx0337'	Internal CIM error.	Call IBM Service.	CEACMDSUNINITERROR
X'xxxx0338'	Internal CEA error.	Call IBM Service.	CEAFILTERBADCOMBO
X'xxxx0339'	Underlying command did not complete in the time specified.	Increase timeout value in the CIM method request and retry request.	CEACMDSTIMEDOUT

Related links

CIM Event Model White Paper

<http://www.dmtf.org/standards/documents/CIM/DSP0107.pdf>

CIM Query Language Specification

http://www.dmtf.org/sites/default/files/standards/documents/DSP0202_1.0.0.pdf

Common Information Model (CIM) Standards

<http://www.dmtf.org/standards/cim>

DMTF website

<http://www.dmtf.org>

DMTF DSP0226: Web Services for Management (WS-Management) Specification

http://www.dmtf.org/sites/default/files/standards/documents/DSP0226_1.0.0.pdf

DMTF DSP0227: WS-Management CIM Binding Specification

http://www.dmtf.org/sites/default/files/standards/documents/DSP0227_1.0.0.pdf

DMTF DSP0230: WS-CIM Mapping Specification

http://www.dmtf.org/sites/default/files/standards/documents/DSP0230_1.0.1.pdf

eServer Common Information Model

http://publib.boulder.ibm.com/infocenter/eserver/v1r1/en_US/info/ciminfo/eicah.pdf

LookAt website for online message explanations

<http://www.ibm.com/systems/z/os/zos/bkserv/lookat/>

OpenPegasus website

<http://www.openpegasus.org>

SNIA website

<http://www.snia.org/>

SourceForge.net

<http://sourceforge.net/>

Specification for CIM Operations over HTTP

http://www.dmtf.org/standards/published_documents/DSP0200_1.3.0.pdf

Storage Management Initiative Specification (SMI-S)

http://www.snia.org/tech_activities/standards/curr_standards/smi/

WBEM standards

<http://www.dmtf.org/standards/wbem>

Web Services for Management

http://dmf.org/sites/default/files/standards/documents/DSP0226_1.1.pdf

WS-CIM Mapping specification

http://dmf.org/sites/default/files/standards/documents/DSP0230_1.0.2.pdf

| **WS-Management CIM Binding Specification**

| [http://dmtf.org/sites/default/files/standards/documents/
| DSP0227_1.1.0.pdf](http://dmtf.org/sites/default/files/standards/documents/DSP0227_1.1.0.pdf)




z/OS information updates on the web

[http://publibz.boulder.ibm.com/cgi-bin/bookmgr_OS390/BOOKS/
ZIDOCMST/CCONTENTS](http://publibz.boulder.ibm.com/cgi-bin/bookmgr_OS390/BOOKS/ZIDOCMST/CCONTENTS)

Legend for graphics showing class structures

The graphics in this book showing class structures illustrate the CIM object modeling using the UML syntax:

Table 9. UML syntax

Construct	Description	Syntax			
association	A relationship between two or more classifiers that involves connections among their instances.				
aggregation	A special form of association that specifies a whole-part relationship between the aggregate (whole) and the component part.				
inheritance	A relationship among classes where one class shares the structure and/or behavior defined for one or more other classes. Inheritance is the mechanism that makes generalization, subclasses, and superclasses possible.				
class	Denotes the representation of a CIM class in UML notation with title, properties, and methods.	<table><tr><td>Title</td></tr><tr><td>Properties</td></tr><tr><td>Methods</td></tr></table>	Title	Properties	Methods
Title					
Properties					
Methods					

How to read syntax diagrams

The following rules apply to the syntax diagrams used in this book:

Arrow symbols

Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

The arrow symbols indicate the beginning and the end of a statement.



Conventions

- Variables are shown in italics, for example, *column-name*. They represent user-defined parameters or suboptions.
- When entering commands, separate parameters and keywords by at least one blank if there is no intervening punctuation.
- Enter punctuation marks (slashes, commas, periods, parentheses, quotation marks, equal signs) and numbers exactly as given.


Required items

Required items are displayed on the horizontal line (the main path).



Optional items


Optional items normally are shown below the main path.




Multiple required or optional items

If you can choose from two or more items, they are displayed vertically in a stack.

If you *must* choose one of the items, one item of the stack is on the main path.




If choosing one of the items is optional, the entire stack is below the main path.



Repeatable items

An arrow returning to the left, above the main line, indicates that an item can be repeated.



A repeat arrow above a stack indicates that you can repeat the items in the stack.

Keywords

- Keywords are shown in uppercase (for example, FROM). They specify field names in the field table and must be substituted by the field ID when coded.
- Variables are shown in all lowercase letters (for example, *column name*). They represent user-supplied names or values. Variables enclosed in quotes must be coded as character strings.
- If punctuation marks, parentheses, arithmetic operators, or other such symbols are shown, you must enter them as part of the syntax.

Accessibility

Publications for this product are offered in Adobe Portable Document Format (PDF) and should be compliant with accessibility standards. If you experience difficulties when using PDF files, you may view the information through the z/OS Internet Library website or the z/OS Information Center. If you continue to experience problems, send an email to mhvrdfs@us.ibm.com or write to:

IBM Corporation
Attention: MHVRCFS Reader Comments
Department H6MA, Building 707
2455 South Road
Poughkeepsie, NY 12601-5400
U.S.A.

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, to use software products successfully. The major accessibility features in z/OS enable users to:

- Use assistive technologies such as screen readers and screen magnifier software
- Operate specific or equivalent features using only the keyboard
- Customize display attributes such as color, contrast, and font size

Using assistive technologies

Assistive technology products, such as screen readers, function with the user interfaces found in z/OS. Consult the assistive technology documentation for specific information when using such products to access z/OS interfaces.

Keyboard navigation of the user interface

Users can access z/OS user interfaces using TSO/E or ISPF. Refer to *z/OS TSO/E Primer*, *z/OS TSO/E User's Guide*, and *z/OS ISPF User's Guide Vol I* for information about accessing TSO/E and ISPF interfaces. These guides describe how to use TSO/E and ISPF, including the use of keyboard shortcuts or function keys (PF keys). Each guide includes the default settings for the PF keys and explains how to modify their functions.

z/OS information

z/OS information is accessible using screen readers with the BookServer or Library Server versions of z/OS books in the Internet library at:

<http://www.ibm.com/systems/z/os/zos/bkserv/>

Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information about the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Mail Station P300
2455 South Road
Poughkeepsie New York 12601-5400
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan, Ltd.
1623-14, Shimotsuruma, Yamato-shi
Kanagawa 242-8502 Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL

BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

If you are viewing this information softcopy, the photographs and color illustrations may not be visible.

Programming Interface Information

This book is intended to help the customer to use the Common Information Model to write system management applications for z/OS systems.

The book also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of CIM.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com)[®] are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both. If these and other IBM trademarked terms are marked on their first occurrence in this information with a trademark symbol ([®] or [™]), these symbols indicate U.S. registered or common law trademarks owned by IBM at the time this information was published. Such trademarks may also be registered or common law trademarks in other countries. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at <http://www.ibm.com/legal/copytrade.shtml>.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Other company, product, or service names may be trademarks or service marks of others.

Terms and conditions for downloading and printing publications

Permissions for the use of the publications you have selected for download are granted subject to the following terms and conditions and your indication of acceptance thereof.

Personal Use: You may reproduce these Publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative works of these Publications, or any portion thereof, without the express consent of IBM.

Commercial Use: You may reproduce, distribute and display these Publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these Publications, or reproduce, distribute or display these Publications or any portion thereof outside your enterprise, without the express consent of IBM.

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the Publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the Publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations. IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

All material copyrighted by IBM Corporation.

By downloading or printing a publication from this site, you have indicated your agreement with these terms and conditions.

Policy for unsupported hardware

Various z/OS elements, such as DFSMS, HCD, JES2, JES3, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

Index

Special characters

_BPX_JOBNAME 49, 69
_BPX_SHAREAS 28, 62

A

accessibility 349
ADDUSER command 25
administrator access 28
ALTUSER command 25
APPL 35
Application Transparent Transport Layer
Security
 See AT-TLS
ARM 39, 70
 element name 71
 policy 71
 security 36
ASCII 65, 276
ASCII-EBCDIC conversion 323
association
 classes 102, 103, 125
 provider function 275
AT-TLS 11, 12, 29
audit logging 69
authentication 11, 12, 28
 based on SSL certificates 31
authorization 11, 13, 25, 42
 check 43
 model 25
 model, provider-based 43
 of users 20
automatic restart 70
Automatic Restart Manager
 See ARM

B

backup
 CIM server configuration 70
 CIM server repository 73
Base classes 121, 126
BaseBoard classes 121, 138
BPX.DAEMON 27
BPX.JOBNAME 62
BPX.POE 35
BPX.SERVER 20, 25
BPX.SMF 69
BPX.SRV 25, 29

C

CDT 24
CDTINFO 24
CEA 38, 39, 41, 339
certificate 11, 29, 30, 31
Certificate Authority 30
CFRM 39
CFZAPPL 35

CFZARMP 71
CFZCIM 19, 21, 49, 61, 69, 70
 customization 49
 start 61
 stop 61
CFZIVP 19, 22
CFZRCUST 19, 20
 customization 46
CFZRCUST parameter
 -noDS 48
 -noSpaceCheck 47, 48
CFZSEC 19, 327
 step BASICSUP 327
 step CRUSR 328
 step CRWBEM 329
 step ENCLCDS 334
 step ENRMF 337
 step ENSMIS 335
 step ENSTC 332
 step ENTCHIP 336
 step ENWLM 336
 step PEAPPL 331
 step PECEA 333
 step PEUSR 330
 step SETARM 331
CFZSRV 20, 25
CFZSRVGP 25
CIM
 introduction 3
CIM client 4, 5
 authentication 29, 31
 request 75, 84
CIM client for Java 4
CIM Event Model 7
CIM indication
 See indication
CIM instrumentation 117
CIM listener 9
CIM model 117
CIM operations 84, 125
CIM operations over HTTP 4
CIM provider
 See provider
CIM Query Language 9
CIM registered profile
 HBA 117, 119
 HDR 117
CIM registered profiles 117
 SMI-S 117
CIM Schema 4
CIM server 4
 access 24, 28
 administration 61
 automatic restart 70
 configuration 53
 configuration backup 70
 configuration for audit logging 69
 logging configuration 67
 logon 28
 quick security setup 19
 quick setup 19

CIM server (*continued*)
 request 23
 runtime configuration 29
 runtime environment 28
 runtime environment security 11
 security 11
 security setup 23
 setup 45
 setup verification 19
 start 19, 21, 49, 51, 61
 stop 61
CIM server group
 definition 25
CIM server user 20
 and identity switch 29
 and resource authorization 26
 association with a started task 49
 authorization to register to ARM 36
 definition 25, 26
CIM_AlertIndication 288
CIM_ComputerSystem 127
CIM_ComputerSystemPackage 141
CIM_ControlledBy 234
CIM_DeviceSAPImplementation 234
CIM_ElementSoftwareIdentity 234
CIM_ElementStatisticalData 234
CIM_EthernetPort 156
CIM_FCPort 233
CIM_FCPortStatistics 233
CIM_HostedAccessPoint 234
CIM_HostedFileSystem 151
CIM_Indication 287, 288
CIM_IndicationFilter 9, 290
CIM_IndicationSubscription 9, 291
CIM_InitiatorTargetLogicalUnitPath 234
CIM_InstalledSoftwareIdentity 234
CIM_InstIndication 287, 289
CIM_InstModification 289
CIM_IPProtocolEndpoint 156
CIM_ListenerDestinationCIMXML 9,
 289, 290
CIM_LocalFileSystem 151
CIM_LogicalDisk 147
CIM_OperatingSystem 127
CIM_OSProcess 127
CIM_PortController 233
CIM_PortImplementsEndpoint 156
CIM_Process 128
CIM_ProcessClassIndication 287
CIM_ProcessIndication 288
CIM_Processor 143
CIM_Product 233
CIM_ProductElementComponent 235
CIM_ProtocolEndpoint 233
CIM_RemoteFileSystem 151
CIM_RunningOS 128
CIM_SNMPTrapIndication 289
CIM_SoftwareIdentity 233
CIM_StorageExtent 233
CIM_SystemDevice 143, 156, 235
cimcli 84

- cimcli (*continued*)
 - a, associators 85
 - an, associatorNames 86
 - ci, createInstance 87
 - dc, deleteClass 88
 - di, deleteInstance 89
 - dq, deleteQualifier 90
 - ec, enumerateClasses 91
 - ei, enumerateInstances 92
 - eq, enumerateQualifiers 93
 - gc, getClass 94
 - gi, getInstance 95
 - gq, getQualifier 96
 - im, invokeMethod 97
 - instance specification 109
 - mi, modifyInstance 98
 - nc, enumerateClassNames 99
 - ni, enumerateInstanceNames 100
 - ns, enumerateNamespaces 101
 - options 107
 - r, references 102
 - rn, referenceNames 103
 - sp, setProperty 104
 - ti, testInstance 105
 - xq, execQuery 106
- cimconfig 63, 64, 79
 - options 53
- CIMIVP 57
- cimmo 77
- cimprovider 43, 81
- CIMSERV 11, 13, 25, 28, 75
 - definition 24
- cimserver command 62
- cimserver_planned.conf 70
- cimserver.env 17, 18, 49, 51, 61, 70
- cimserver.err 49
- cimserver.out 49
- cimserver.trc 65
- cimsub 110
- class descriptor table 24
- class SURROGAT 25
- client 4, 5
 - authentication 29, 31
 - user 29
- Cluster classes 122, 191
- Cluster provider setup 38
- CMPI 271
 - header files 272
- CMPI provider
 - function signatures 274
 - initialization 274
 - samples 285
 - security 275
- command-line utilities 75
- commands 75
- comments
 - how to send your comments to IBM xiii
- Common Area Data Space 39
- Common Event Adapter
 - See CEA
- Common Information Model
 - See CIM
- Common Manageability Programming Interface
 - See CMPI
- compilation 77

- concepts of CIM 3
- configuration properties 53
 - dynamic 53, 63
 - for tracing 64
 - modification 113
 - modification, current 63
 - modification, planned 63, 113
- configuration property
 - daemon 53
 - enableAuditLog 53, 69
 - enableHttpConnection 53
 - enableHttpsConnection 29, 54
 - enableIndicationService 54
 - enableRemotePrivilegedUserAccess 54
 - forceProviderProcesses 54, 62, 285
 - httpPort 45, 54
 - httpsPort 29, 45, 54
 - idleConnectionTimeout 54
 - logLevel 54, 67, 68
 - maxFailedProviderModuleRestarts 55
 - maxProviderProcesses 55
 - messageDir 55
 - providerDir 55
 - repositoryDir 55
 - repositoryIsDefaultInstanceProvider 55
 - shutdownTimeout 55
 - slp 55
 - socketWriteTimeout 55
 - traceComponents 56, 64
 - traceFacility 56, 65, 67
 - traceFilePath 56, 65
 - traceLevel 56, 64
 - traceMemoryBufferKbytes 56, 65
- connectivity 117
- console 67, 70, 113
- contacting IBM xiii
- CoupleDataset provider setup 38
- CQL 9
- createClass 84
- current configuration property 63, 79

D

- daemon configuration property 53
- data encryption 11
- DDNAME 49
- DDS 37, 51, 52
- DeliveryRetryAttempts property 8
- DeliveryRetryInterval property 8
- designated user 13, 25, 42, 275
- DesignatedUserContext property 43, 276
- directory paths 20
 - base hierarchical file system 17
 - CIM client for Java 17
 - CIM message files for NLS 17
 - CIM provider libraries provided with z/OS 17
 - CIM schema master repository 17
 - CIM server executables 17
 - CIM server libraries 17
 - configuration files 48
 - data repository 48
 - DMTF CIM schema files (MOF) 17
 - IBM z/OS instrumentation MOF files 17
 - log 48
 - sample profile 17

- directory paths (*continued*)
 - SMP/E target library path 17
 - started task environment 48
- disability 349
- Distributed Data Server
 - See DDS
- Distributed Management Task Force
 - See DMTF
- DMTF xi, 3
- dynamic
 - CDT 24
 - configuration property 53, 63
- dynamic load library 13
 - program control 13

E

- EBCDIC 276, 323
- ELEMTERM termination type 71
- enableAuditLog configuration
 - property 53, 69
- enableHttpConnection configuration
 - property 53
- enableHttpsConnection configuration
 - property 29, 54
- enableIndicationService configuration
 - property 54
- enableRemotePrivilegedUserAccess
 - configuration property 54
- encryption 11, 29, 31
 - key 35
- Enhanced ASCII 323
- Enhanced Security model 13, 25
- EnumerateInstanceNames 125
- EnumerateInstances 125
- environment variable 51
 - _BPX_JOBNAME 69
 - _BPX_SHAREAS 28
 - LIBPATH 51
 - OSBASE_TRACE 51
 - OSBASE_TRACE_FILE 51
 - PATH 51
 - PEGASUS_HOME 50, 51
 - RMF_CIM_BENCH 52
 - RMF_CIM_HOST 51
 - RMF_CIM_PORT 52
 - RMF_CIM_PROVIDER 51
 - RMF_CIM_TRACE 52
 - RMF_CIM_TRACE_FILE 52
 - RMF_INDICATION
 - _POLLING_INTERVAL 52
 - RMF_INDICATION_RESTTIME 52
 - WLM_CIMPROVIDER
 - _TRACE_FILE 52
 - WLM_CIMPROVIDER
 - _TRACE_LEVEL 52
- environment variables
 - file cimserver.env 17, 49, 51, 70
 - file profile.add 49, 50, 323
 - modification 51
- EOTRACE 65
- error messages 323
- eServer CIM 6
- event 7
 - subscription 7
- Event Model 7
- event provider function 275

extattr 27

F

fallback 18
FATAL log level 67
file system 20
File System classes 121, 150
filter condition 7
forceProviderProcesses configuration
property 54, 62, 285

G

GetInstance 125
GID
definition, CIM server 25
group ID
See GID

H

HBA 117, 119
Hot Swap Events 119
instance diagram 119
HDR 117
header files
CMPI 272
host adapter 117
Host Discovered Resources
instance diagram 118
profile 117
Host-Bus-Adapter
See HBA
HTTP 21, 28
HTTP port 45
HTTP_NOAUTH 37
httpPort
configuration property 45
httpPort configuration property 45, 54
HTTPS 21, 28, 29
HTTPS port 45
httpsPort
configuration property 45
httpsPort configuration property 29, 54

I

IBM_BaseBoard 139
IBMzOS
_SBDeviceSAPImplementation 256
IBMzOS
_SBInitiatorTargetLogicalUnitPath 149, 258
IBMzOS_BaseBoard 140
IBMzOS_CFRMCoupleDataset 192
IBMzOS_CFRMPolicy 194
IBMzOS_CFStrDependsOn 228
IBMzOS_CFStructure 196
IBMzOS_CFStructureConnector 206
IBMzOS_CollectionOfCFs 228
IBMzOS_CollectionOfSysplexNodes 229
IBMzOS_ComputerSystem 129
IBMzOS_ControlledBy 249
IBMzOS_CoupleDataset 209

IBMzOS_CouplingFacility 213
IBMzOS_CouplingFunction 217
IBMzOS_CSBaseBoard 141
IBMzOS_CSFCPort 250
IBMzOS_CSFCPortController 251
IBMzOS_ElementSoftwareIdentity 252
IBMzOS_EthernetPort 157
IBMzOS_FCPort 236
IBMzOS_FCPortStatisticalData 253
IBMzOS_FCPortStatistics 239
IBMzOS_HostedCFStrConnector 230
IBMzOS_HostedCFStructure 229
IBMzOS_InstalledSoftwareIdentity 254
IBMzOS_IPProtocolEndpoint 158
IBMzOS_JES2Job 161
IBMzOS_JES2SysoutDataset 180
IBMzOS_JES3Job 171
IBMzOS_JES3SysoutDataset 183
IBMzOS_Job 184
IBMzOS_JobsManagementSettings 185
IBMzOS_LogicalDisk 148
IBMzOS_LogicalDiskDevice 149
IBMzOS_NFS 153
IBMzOS_OperatingSystem 131
IBMzOS_OSProcess 133
IBMzOS_PortController 241
IBMzOS_Process 134
IBMzOS_Processor 144
IBMzOS_Product 243
IBMzOS_ProductElementComponent 255
IBMzOS_RunningOS 136
IBMzOS_SBHostedAccessPoint 257
IBMzOS_SBProtocolEndpoint 244
IBMzOS_SFMAAttributes 220
IBMzOS_SoftwareIdentity 246
IBMzOS_Subsystem 186
IBMzOS_SubsystemJES2Jobs 189
IBMzOS_SubsystemJES3Jobs 189
IBMzOS_SysoutDataset 188
IBMzOS_Sysplex 221
IBMzOS_SysplexCoupleDataset 224
IBMzOS_SysplexNode 225
IBMzOS_UnixLocalFileSystem 152
IBMzOS_UnixProcess 137
IBMzOS_UsesCFRMCoupleDatasets 231
IBMzOS_UsesCFRMPolicies 231
IBMzOS_UsesCFs 230
IBMzOS_UsesCouplingFunctions 231
IBMzOS_UsesJES2SysoutDatasets 189
IBMzOS_UsesJES3SysoutDatasets 189
IBMzOS_UsesSysplexCoupleDatasets 231
IBMzOS_WLM 262
IBMzOS_WLMOS 267
ICHRIN03 started procedures table 49
identity switch 29
idleConnectionTimeout configuration
property 54
indication 7, 287
end point 33
hierarchy 287
polling interval 52
provider 9
provider function 275
secured 33
stream 289, 290
subscription 52, 289
indication delivery retry 8

INFORMATION log level 67
installation 17
directories 17
verification 19, 22, 57
installation verification program
See IVP
instance provider function 274
introduction to CIM 3
IOS service 41
IOSCDR 41
IOSCHPD 41
IVP 19, 22, 57
IXCARM 36
IXCL1DSU format utility 39

J

Java
CIM client 4
JES2Job provider setup 38
JES3Job provider setup 38
Job classes 122, 160

K

key 30, 35
key ring 30
keyboard 349

L

LIBPATH environment variable 17, 51
lifetime 8
log 67
level 68
FATAL 67
INFORMATION 67
SEVERE 67
TRACE 67
WARNING 67
level modification 67
message 65, 67, 68
records for audit logging 69
routing 66
logging 67, 68
See log
Logical Disk classes 146
logical storage resource 117
logLeve lconfiguration property 68
logLevel configuration property 54, 67
LogMessages trace component 66, 67
logon
to the CIM server 28, 35

M

managed object format
See MOF
management instrumentation
for additional z/OS resources 271
master repository 17
maxFailedProviderModuleRestarts
configuration property 55
maxProviderProcesses configuration
property 55

- memory dump 65
- message
 - shutdown 70
 - startup 70
- messageDir configuration property 55
- messages 295
 - troubleshooting 323
- method provider function 275
- migration 17
- MLS 35, 54
- MODIFY console command 63, 64, 113
- modifyClass 84
- modifyInstance 84
- ModuleGroupName 63, 285
- MOF 75
 - compiler 77
 - file, provider registration 43
- monitoring provider 51
- multi level security
 - See* MLS
- must-stay-clean 26

N

- Network classes 122, 154
- Network provider setup 38
- NOOIDCARD attribute 25
- NOPASSWORD attribute 25
- NOPHRASE attribute 25

O

- oidcard 42
- OOP
 - See* out-of-process support
- OpenPegasus 4
- OS (operating system) 5
- OS management
 - Base classes 121, 126
 - BaseBoard classes 121, 138
 - Cluster classes 122, 191
 - File System classes 121, 150
 - Job classes 122, 160
 - Logical Disk classes 146
 - Network classes 122, 154
 - Processor classes 121, 142
- OSBASE_TRACE 51
- OSBASE_TRACE_FILE 51
- out-of-process support 26, 54, 62
 - developing providers OOP 285
 - tracing providers 65

P

- PARMLIB 39
- passphrase 42
- PassTicket 11
 - authentication 37
 - keymask 20
 - passkey 20
 - validation 35
- password 11
- PATH 51
- PEGASUS_HOME 50, 51
- PEGASUSMEMTRACE 65
- performance benchmark 52

- performance implications 65
- PG_Provider 43, 277, 280
- PG_ProviderCapabilities 277, 283
- PG_ProviderModule 43, 277, 281
- planned configuration property 63, 79
 - file cimserver_planned.conf 70
- policy
 - inbound 31, 32
 - outbound 32, 33
- Policy Agent 29
 - setup 30
- port 45
- port 5980 21
- port 5988 21
- port number 45
- POSIT 24, 329
- PreviousInstance 289
- PreviousInstance property 288
- priority for z/OS CIM 52
- privileged user 25, 26
- Processor classes 121, 142
- profile.add 49, 50, 323
- program control 27
- protected user
 - definition 25
- protection of resources 11
- provider 4
 - based authorization 13, 43
 - CMPI 271
 - development 271
 - disabling 81
 - enabling 81
 - function signatures 274
 - function, association 275
 - function, indication 275
 - function, instance 274
 - function, method 275
 - IBM-supplied 121
 - initialization 274
 - listing 81
 - profile 13
 - registration 277
 - registration compilation 77
 - registration MOF file 43, 285
 - registration processing 278
 - registration schema 277
 - removal 81
 - RMF 51
 - samples 285
 - security 275
 - setup 38, 39
 - trace 65
 - WLM 52
- provider agent 26, 65, 285
- providerDir configuration property 55
- ProviderModuleName 280
- PTKTDATA 35, 37
- publish/subscribe event paradigm 8

R

- RACF 23, 37
 - class definition 24
 - class WBEM 24
 - profile definition 24
 - setup 39
- reason codes 339

- repository 17, 55, 77
 - backup 73
 - maintenance 73
 - recovery 73
- repositoryDir configuration property 55
- repositoryIsDefaultInstanceProvider
 - configuration property 55
- requestor 23, 25, 42
 - user ID 42
- resource
 - access 42
 - authorization model 25
- Resource Access Control Facility
 - See* RACF
- Resource Measurement Facility
 - See* RMF
- restart
 - automatic restart using ARM 70
- REXX 39
- RMF 28
 - provider 51
- RMF monitoring 37
- RMF_CIM_BENCH 52
- RMF_CIM_HOST 37, 51
- RMF_CIM_PORT 52
- RMF_CIM_PROVIDER 51
- RMF_CIM_TRACE 52
- RMF_CIM_TRACE_FILE 52
- RMF_INDICATION
 - _POLLING_INTERVAL 52
- RMF_INDICATION_RESTTIME 52
- runtime
 - configuration 29
 - environment 28
 - environment security 11

S

- SAF 11, 29, 30, 32, 36, 43, 69, 280, 299, 306, 307, 308, 309
- SAF profile
 - BPX.SERVER 20, 25
 - BPX.SMF 69
 - CFZAPPL 35
 - CIMSERV 24, 28
- SAF profiles
 - security 43
- SB Multipath Management
 - profile 117, 118
- SBLIM 4, 285
- security 11
 - aspects for developing providers 275
 - context 42
 - of the network 12
 - profile 11, 13, 43
 - quick setup for the CIM server 19
 - setup for CIM server 23
 - setup for the CIM server, quick 19
 - using ARM 36
- SecurityAccessProfile 43, 277, 280
- sequence identifier 8
- service class for CIM priority 52
- SEVERE log level 67
- ShareAS 63, 285
- shortcut keys 349
- shutdown message 70

- shutdownTimeout configuration
 - property 55, 113
- slp configuration property 55
- SMF
 - configuration 69
 - record 53, 69
- SMI-S 117
 - profile 117
- SMP/E installation 17, 71
- SNIA 117
- socketWriteTimeout configuration
 - property 55
- SourceInstance 289
- SSL 11, 29
 - protected indication delivery 33
 - protection including certificate based authentication 31
 - simple protection 31
- STARTED class 49
- started task 25, 49
 - CFZCIM 61
 - CFZCIM customization 49
- starting the CIM server 19, 21, 61
- startup message 70
- STDENV 49
- stderr 67
- STDERR 49
- STDOUT 49
- stopping the CIM server 61
- storage
 - device 117
 - hardware resources 117
 - network 117
- Storage HBA
 - profile 117, 119
- storage management 41
- Storage management classes 233
- Storage Management Initiative
 - Specification
 - See* SMI-S
- Storage Networking Industry Association
 - See* SNIA
- subscription 7
- SURROGAT class 25, 29
- surrogate 29
- switching identity 29
- syntax check 77
- syntax diagram 347
 - cimcli 84
 - cimconfig 79
 - cimmof 77
 - cimprovider 81
 - cimsub 110
 - MODIFY 113
- syslog
 - configuration file 68
 - daemon 67, 68
 - configuration 69
 - level 68
 - service 68
- syslog.conf 68
- sysplex 36, 70
- SYSREXX support 39
- System Authorization Facility
 - See* SAF
- system logger
 - See* syslog

T

- TCP/IP 21
 - address 51
 - hostname 51
 - port number 52
- termination type 71
- The Open Group 4
- trace 64
 - buffer size 65
 - components 64
 - configuration 64
 - disabling 66
 - enabling 64
 - facility 65, 67
 - file 51, 52, 65
 - file name 66
 - level 51, 64
 - level for the RMF CIM provider 52
 - level for the z/OS WLM provider 52
 - message 65, 67
 - modification 64
 - providers 65
 - routing 66
 - variable 51
- trace component
 - All 64, 65
 - Authentication 64
 - Authorization 64
 - BinaryMessageHandler 64
 - CIMExportRequestDispatcher 64
 - CIMOMHandle 64
 - CMPIProvider 64
 - CMPIProviderInterface 64
 - Config 64
 - ControlProvider 64
 - CQL 64
 - DiscardedData 64, 65
 - Dispatcher 64
 - ExportClient 64
 - Http 64
 - IndicationFormatter 64
 - IndicationGeneration 64
 - IndicationHandler 64
 - IndicationReceipt 64
 - IndicationService 64
 - IPC 64
 - L10N 64
 - Listener 64
 - LogMessages 64, 65
 - MessageQueueService 64
 - ObjectResolution 64
 - OsAbstraction 64
 - ProviderAgent 64
 - ProviderManager 64
 - Repository 64
 - Server 64
 - Shutdown 64
 - SSL 64
 - StatisticalData 64, 65
 - Thread 64
 - UserManager 64
 - WQL 64
 - WsmServer 64
 - Xml 64
 - XmlIO 64, 65
- TRACE log level 67

- traceComponents configuration
 - property 56, 64, 67
- traceFacility configuration property 56, 65, 67
- traceFilePath configuration property 56, 65, 66
- traceLevel configuration property 56, 64
- traceMemoryBufferKbytes configuration
 - property 56, 65
- tracing
 - See* trace
- troubleshooting 323

U

- UID 20, 25, 26
- UNIX
 - file system 20
 - System Services command
 - prompt 51, 62
 - System Services shell 21, 49, 50, 75, 84
- user 23
 - access 28
 - authorization 20
 - certificate 11
 - context 42, 275
- user ID 11, 23
 - CIM server user ID switch 29
 - client 29
 - definition, CIM server 25
 - designated 13, 42
 - privileged 25
 - protected 25
 - requestor 42
- user identity
 - See* user ID
- UserContext 43
- UTF-8 276

V

- velocity goal 52
- verification
 - CIM server startup 22, 61, 62
 - customization 22, 57
 - installation 22, 57

W

- WARNING log level 67
- WBEM xi, 3, 13, 24
- wbemexec 76
- Web Based Enterprise Management
 - See* WBEM
- Web Services for Management 4
 - See* WS-Management
- WLM
 - classes 262
 - provider 52
 - service class for CIM priority 52
- WLM management 40
- WLM_CIMPROVIDER_TRACE_FILE 52
- WLM_CIMPROVIDER_TRACE_LEVEL 52
- Workload Manager 262
 - See* WLM

World Wide Port Number
 See WWPN
WS-Enumeration 4
WS-Management xv, 4
WS-Transfer 4
WWPN 41, 244

X

XCF address space
 See XCFAS
XCFAS 36

Z

z/OS Communications Server 125
 system logger
 See syslog
z/OS Security Server 24, 28
z/OS system console
 See console
zFS data set 46



Product Number: 5694-A01

Printed in USA

SC33-7998-08

