

HTC VIVE Tracker (2018) Developer Guidelines Ver. 1.4

Version Control

Version Number	Version Date	Version Reason
1.0	2018.01.19	Initial version for VIVE Tracker (2018)
1.1	2018.3.6	Revision
1.2	2018.12.19	Add USB button event
1.4	2019.3.8	Add FAQ.9

©2019 HTC Corporation. All Rights Reserved. HTC, the HTC logo, VIVE, the VIVE logo, and all other HTC product and services names are the trademarks or registered trademarks of HTC Corporation and its affiliates in the U.S. and other countries.

Contents

- Introduction 1
 - Use cases..... 1
- Hardware requirements..... 3
 - Interface..... 4
 - Radio frequency (RF)..... 5
 - Power 6
 - Optics 6
 - Docking..... 7
- Mechanical considerations..... 11
 - Apparel size 12
 - Main feature..... 13
 - Docking mechanism..... 14
 - Damping mechanism 16
 - Accessory design..... 17
 - Coordinate system..... 23
- Software components 26
 - System requirements 26
 - Data formats 28
 - Accessory integration..... 31
 - Unity integration..... 36
 - VIVE Trackers and VIVE Roles..... 45
 - Tracker on Unity or Unreal..... 47
 - Firmware upgrade..... 47
- FAQs..... 48

Introduction

This document describes the development guidelines for VR accessory makers and content developers. It contains information on how to use the HTC VIVE Tracker (2018) to enable position tracking and transmission of specific data (with or without the HTC VIVE VR system).

VIVE Tracker (2018) can pair with HTC’s wireless dongle or use its USB interface to transfer tracking data to a PC. An accessory attached to VIVE Tracker (2018) can:

- Simulate buttons of the VIVE controller through the underlying Pogo pin.
- Send specific data to a PC via the USB interface of VIVE Tracker (2018) or use its original approach for transferring data.

Use cases

There are five use cases supported by VIVE Tracker (2018).

Use Case 1: Track passive objects with a USB cable in VR. In this case, the dongle is not used, and VIVE Tracker (2018) connects with a PC by USB directly to transfer tracking data.




Figure: Use case 1 of VIVE Tracker (2018)

Use Case 2: Track passive objects using a USB cable interface in VR, with the accessory passing data to a PC through USB, BT/Wi-Fi or propriety RF. This case is similar to Use Case 1, but the accessory transfers data to PC directly for a specific purpose based on its design.




Figure: Use case 2 of VIVE Tracker (2018)

Use Case 3: Track moving objects by wireless interface in VR. In this case, the dongle is used to transfer tracking data from the VIVE Tracker (2018) to a PC.




Figure: Use case 3 of VIVE Tracker (2018)

Use Case 4: Track moving objects using a wireless interface in VR, with the accessory passing data to a PC via USB, BT/Wi-Fi or propriety RF. This case is similar to Use Case 3, but the accessory transfers data to/from a PC directly for a specific purpose based on its design.




Figure: Use case 4 of VIVE Tracker (2018)

Use Case 5: Track moving objects using a wireless interface in VR, with the accessory simulating buttons of the VIVE controller or passing data to a PC via the VIVE Tracker (2018). This case is similar to Use Case 3, but the accessory connects with the VIVE Tracker (2018) to transfer a button event to a PC through the Pogo pin or the USB interface.




Figure: Use case 5 of VIVE Tracker (2018)

Hardware requirements

This section describes hardware requirements for accessories used with the VIVE Tracker (2018) in order to enable position tracking and input of specific data for the HTC VIVE VR system.

A compatible accessory may be attached to the VIVE Tracker (2018) to send specific data to a PC through the USB interface of the VIVE Tracker (2018). The VIVE Tracker (2018) needs to pair with the dongle to transfer an event to a PC. The figure below describes the conceptual architecture.




Figure: Conceptual Architecture of VIVE Tracker (2018)

Interface

USB 2.0 full speed (client) from micro USB connector.

	Pin no.	Type	Description
	1	Digital output	General purpose output pin
	2	GND	Ground
	3	Digital/Power input	General purpose input pin: Internal pullup resistor to VDD, Active-low (Trip button) Power input pin
	4	Digital input	General purpose input pin: Internal pullup resistor to VDD, Active-low (Trigger button)
	5	Digital input	General purpose input pin: Internal pullup resistor to VDD, Active-low (Trackpad button)
6	Digital input	General purpose input pin: Internal pullup resistor to VDD, Active-low (Menu button)	

Absolute Maximum Rating

Symbol	Parameter	Min	Max	Unit
V_I	Input voltage	- 0.5	3.6	V
V_{ESD}	Electrostatic discharge voltage, Human Body Model	--	4000	V

Electrical Characteristics (Supply voltage VDD = 3.3 V)

Symbol	Parameter	Min	Typ	Max	Unit
V_{OH}	High-level output voltage	$VDD - 0.4$	--	--	V
V_{OL}	Low-level output voltage	--	--	0.4	V
V_{IH}	High-level input voltage	$0.7VDD$	--	--	V
V_{IL}	Low-level input voltage	--	--	$0.3VDD$	V
I_{OH}	High-level output current	20	--	--	mA
I_{OL}	Low-level output current	4	--	--	mA
I_{IH}	High-level input current	--	0.5	10	nA
I_{IL}	Low-level input current	--	0.5	10	nA

Radio frequency (RF)

To establish a stable wireless connection between the VIVE Tracker (2018) and the dongle, the OTA performance of VIVE Tracker (2018) cannot downgrade to more than 3dB when an accessory is attached to the VIVE Tracker (2018).

The following are recommendations for better RF performance:

Except for essential parts, such as the 1/4" screw, electric connection pad (which connects with the Pogo pin), and related circuits of the electric connection pad, metal parts of the accessory should keep at least 30mm distance away from the antenna to avoid OTA performance reduction when the accessory is attached to VIVE Tracker (2018).

The figure below illustrates the “keep out” area where only nonmetallic parts of the accessory should be inside (spherical radius=30mm and the center is antenna feed point).




Figure: Restricted Area of Antenna

Power

Micro USB Connector	Voltage requirement	Max Charging current	Max Charging time
AC	5V+/-5%	1000 mA	2 hrs
PC		500 mA	3 hrs

Pogo Pin 3	Voltage requirement	Max Charging current	Max Charging time
PC	5V+/-5%	500 mA	3 hrs

Note

AC: D+ short to D-

PC: D+/D- communication

Table: Micro USB connector and Pogo pin indication

Optics

The field of view (FOV) of VIVE Tracker (2018) is 270 degrees. Avoid placing the structure within the view angle, since it will block responses from VIVE Tracker (2018) sensors when placed in that direction.

If the docking part extends beyond the recommended placing cone, extra views will be blocked.




Figure: Docking part extends beyond recommended placing cone


Docking

The following are requirements for docking compatibility:

- a. The docking design of VIVE Tracker (2018) follows the ISO standard (ISO 1222:2010). Furthermore, VIVE Tracker (2018) has constraining features, such as the longer screw cannot fasten all the way in.
- b. The user should be able to easily attach and detach VIVE Tracker (2018) with two hands. One hand holds VIVE Tracker (2018), and the other one holds the accessory.
- c. The user should not be at risk of physical harm while attaching or detaching VIVE Tracker (2018).
- d. The user should be comfortable while attaching and detaching VIVE Tracker (2018).
- e. The accessory attached with VIVE Tracker (2018) should be in the shape of a physical object to avoid hitting during operating.
- f. VIVE Tracker (2018) should not be blocked by the accessory and affect the tracking performance.
- g. It is strongly recommended that the accessory uses low reflection material for its outer skin to avoid reflection interference with the tracking sensors, especially if the accessory needs to be placed within the tracking sensors' FOV area.


Docking embodiments

Gun



Sword

It is recommended to design the mounting mechanism close to the hand-held area, and set up the length in the VR program.




Multi-purpose docking base


Users are able to attach the VIVE Tracker (2018) to any object/surface that is intended to be tracked.

- If the object/surface is smooth and stiff, it is recommended to use stronger adhesive tape for attaching the docking base to the specific object/surface (ex. 3M VHB tape).
- If the object/surface is rough and soft, it is recommended to use a strap for tightening the docking base to the specific object/surface.



Improper VIVE Tracker (2018) placement may cause the accessory body to obstruct the tracking performance. The mounting distance between tracking FOV and the related accessory size is shown below:





Mechanical considerations

This section describes the mechanical considerations for developers to build various accessories that are compatible to fit or mount with the VIVE Tracker (2018).



Figure: VIVE Tracker (2018)

Apparel size




Figure: VIVE Tracker (2018) with different angle

The overall size of the VIVE Tracker (2018) is $\phi 99.65\text{mm} * 42.27\text{mm}$ (height); 89g (weight).

Main feature




Figure: Main features

1. **LED Indicator:** Shows the status of VIVE Tracker (2018).
2. **Power Button:** Used for powering on/off, BLE pairing, etc.
3. **Sensor:** Receives signals from the base stations. The VR system uses the received signals for computing the current location of VIVE Tracker (2018). Accessory should minimize surface reflection (e.g. avoid white color surface) since it may cause faulty signal and affect performance. Anti-reflection painting is preferred.
4. **Docking Mechanism:** Standard camera tripod docking method is used which is comprised of:
 - 4.1 1/4" Screw nut to fasten the accessory.
 - 4.2 Stabilizing pin recess for constraining the tracking from rotation.
 - 4.3 Pogo pin port (spring contact-type) for optional electrical connection to the accessory.
 - 4.4 Friction pad for providing steady friction between the accessory and VIVE Tracker (2018)
5. **USB Port:** Used for electrical connection to the accessory through a micro USB cable.

Docking mechanism

VIVE Tracker (2018) applies the general camera tripod docking method, which follows ISO standards (ISO 1222:2010).

The following are the schematic drawings of how the accessory will mount to the VIVE Tracker (2018).

Docking with standard tripod cradle head (w/o electric connection)




Figure: Docking with standard tripod cradle

VIVE Tracker (2018) can be mounted on the cradle head first, and then attached to the main body of the accessory (similar to how a camera is mounted on a tripod).

Docking with side tightening wheel (w/ electric connection if needed)




Figure: Docking with side tightening wheel

In this example, the mechanical method allows developers to tighten the docking screw through the side spinning wheel. It is recommended that the spinning wheel should have a larger diameter (25 mm or greater) for better operation.

This example is able to use the Pogo pin for extending the electric connection to somewhere else.

Damping mechanism

During research and actual usage, it has been observed that continuous vibration in VIVE Tracker (2018) will affect the IMU performance, causing noticeable IMU drift. To address this, it is suggested to use a damping system with the docking mechanism. The illustration below is a reference for how existing damping rubbers (purchased as a drone accessory) can serve the purpose.



When considering the vibration level that the VR content plans to adopt, among the factors that can be adjusted are the durometer of the damper rubber, the mounting distance/position, and the usage of damper rubbers.


Accessory design

Below are the different accessory mechanisms, following ISO standards:



- 1/4" bolt design
Please refer to ISO 1222-2010, Figure 1 on page 1.
- Stabilizing pin design
VIVE Tracker (2018) leverages the design from ISO 1222-2010, Figure 5 on page 3. For details on dimensions and tolerances, please refer to pages 13-17. It is suggested to apply the Stabilizing Pin for better tracking performance.
- Screw thread design
The screw thread type that applies to VIVE Tracker (2018) is 1/4" screw with 1.27 mm pitch. For detailed information, please refer to ISO 1222-2010, pages 3-5.

Design of Pogo Pin Pad

- a. Pin definition (VIVE Tracker (2018))






b. Pogo Pin Pad reference design
Electrical






Pin no.	Type	Description
1	Digital output	General purpose output pin
2	GND	Ground
3	Digital / Power input	General purpose input pin: Internal pull up resistor to VDD, Active-low (Grip button) Power input pin
4	Digital input	General purpose input pin: Internal pull up resistor to VDD, Active-low (Trigger button)
5	Digital input	General purpose input pin: Internal pull up resistor to VDD, Active-low (Trackpad button)
6	Digital input	General purpose input pin: Internal pull up resistor to VDD, Active-low (Menu button)

Mechanical









Contact Resistance :

30m Ω (Max) initial when measured at 20mV (Max) open circuit at 100mA.

Contact Current Rating :


1.8A (Min)

Coordinate system

VIVE Tracker (2018) uses the **“Right-handed coordinate system”**.


VIVE Tracker (2018)

- Datum A is set to be the top surface of the ring feature around the 1/4” Screw Nut.
- Datum B is set to be the intersection point between the centerline of Standard Camera Mount (1/4” Screw Bolt) and Datum A.
- Datum C is set to be the intersection point between the centerline of Stabilizing Pin Recess and Datum A.
- The coordinate system is constructed by the Datum frame of Datum A, the line of Datum B and Datum C, and Datum C itself.



Accessory:

- Datum A is set to be the top surface of the ring feature around the 1/4" Bolt.
- Datum B is set to be the intersection point between the centerline of 1/4" Screw and Datum A.
- Datum C is set to be the intersection point between the centerline of Stabilizing Pin and Datum A.
- The coordinate system is constructed by the Datum frame of Datum A, the line of Datum B and Datum C, and Datum C itself.



Software components

This section describes software components for the HTC VIVE Tracker (2018).

If you are an accessory maker, you can transfer a button event through the VIVE Tracker (2018) Pogo pin. You may refer to detailed data format transfer between an accessory and VIVE Tracker (2018) in the [Data Formats](#) section.

If you are a content developer, you can refer to [Unity integration](#) and

Accessory integration sections to create virtual reality content for an accessory attached with VIVE Tracker (2018).

When new firmware for VIVE Tracker (2018) is released, you can upgrade the firmware using a PC through USB cable. You can find the steps in the [Firmware upgrade](#) section.

System requirements

For both content developers and accessory makers:

1. To test VIVE Tracker (2018) with your content or accessory, you need to have HTC VIVE as well as the required hardware and software to run it. You can find more information on www.vive.com.
2. You need to have a PC with at least one available USB 2.0 port to plug in the dongle (for use cases with the dongle mentioned in previous section) or VIVE Tracker (2018) (for firmware upgrade purpose). This PC should also run SteamVR for HTC VIVE.




Figure: VIVE Tracker (2018) and PC

For accessory makers:

If your accessory needs to simulate buttons of the VIVE controller or transfer data to a PC through VIVE Tracker (2018), it must support the following interfaces respectively:

Pogo pin

Refer to hardware requirement section for detailed information on button simulation.

USB interface

USB full speed host and HID class. The VIVE tracker will act as a USB device to transfer data to/from the attached accessory.




Figure: VIVE Tracker and accessory USB data transfer


Data formats

This section describes the data formats that accessory makers can use to transfer data between the accessory and the PC through VIVE Tracker (2018) when the USB interface is used.

The data format for transfer from an accessory to VIVE Tracker (2018) is sent by a USB HID feature report. It is similar to the user interface of the VIVE controller. The interval to send data should be longer than 10 ms.

To learn more about the USB HID spec, please refer to information on the official USB website: <https://www.usb.org/hid> VIVE Tracker (2018) will have three USB nodes when connected as a USB device to a PC. Use USB VID/PID as **28DE/2300** for VIVE Tracker (2018), and check that the interface name changes to 'Controller'. Select the wIndex to **2** to send USB commands to VIVE Tracker (2018).

Refer to the table below for the USB command flow between accessory and VIVE Tracker (2018).



SetFeature 0xB3 data format:

Byte Index	Data	Remark
0	Host Type	2 : phone 3 : accessory
1	N/A	Reserved
2	N/A	Reserved

SetFeature 0xB4 data format:

Byte Index	Data	Remark
0	Tag Index	Indicates the version of the data being sent out. Default value is zero in this version of data format.
1	Button	TRIGGER 0x01 BUMPER 0x02 MENU 0x04 STEAM 0x08 PAD 0x10 PAD_FINGERDOWN 0x20 Reserved 0x40 Reserved 0x80
2	Pad X value	Pad X value, value from -32768 to 32767 BYTE 2 is LSB
3		
4	Pad Y value	Pad Y value, value from -32768 to 32767 BYTE 4 is LSB
5		
6	Trigger Raw	Trigger Raw, value from 0 to 65535 BYTE 6 is LSB
7		
8	Battery Level	Battery Level, Reserved BYTE 8 is LSB
9		

Table: Data Format (Accessory to VIVE Tracker (2018))

Sample code:

Below are sample code to send the setFeature command to VIVE Tracker. However, you need to reference your system to have the correct API to send the USB setFeature command.

Visual Studio:

```
buffer[0] = 0xB3;
buffer[1] = 0x03; // Length
buffer[2] = 0x03; // 1: PC, 2: Phone, 3: Accessory
buffer[3] = 0x01;
buffer[4] = 0x00;

if (!HidD_SetFeature(m_hDevice, buffer, sizeof(buffer))) {
    AfxMessageBox(L"Error: Failed to set feature.");
}
```

JAVA:

```
// Take 0xB3 command for example
data1[0] = (byte) 179; //0xB3
data1[1] = 3; //Means there are 3 bytes follow
data1[2] = 3; //Host Type: ACCESSORY
data1[3] = 1; //Reserved
data1[4] = 1; //Reserved

int result = mDeviceConn.controlTransfer(0x21, 0x09, 0x0300, 2, data1, data1.length, 0);
```

STM F4 series developer board:

```
char buffer[64];
char *p_buffer = buffer;
unsigned int buffer_size = sizeof(buffer);
memset( (void *)p_buffer, 0, buffer_size );
p_buffer[0] = 0xB3; // Command
p_buffer[1] = 0x03; // Size of Data
p_buffer[2] = 0x03; // Host Type: ACCESSORY
p_buffer[3] = 0x01;
p_buffer[4] = 0x01;

// STM API
USBH_HID_SetReport(
    handle,
    0x03, // Feature Report
    0,
    (uint8_t *)p_buffer,
    buffer_size );
```

Accessory integration

For Pogo out pin signal duration:

VIVE Tracker (2018) receives haptic input value from the content, while the Pogo out pin will output HIGH with the duration value in “ms”.

This section describes information on position transformation between an accessory and VIVE Tracker (2018). Content developers can create the correct rotation and translation result of the content used with the attached accessory in a game engine such as Unity.

It is assumed that the local coordinate system of the accessory is z-axis facing the front (left-handed coordinate system), and VIVE Tracker (2018) is attached in the accessory as in the example below. Rotation degree and translation distance of an accessory relevant to VIVE Tracker (2018) are described in roll, yaw, pitch and D_x , D_y , D_z respectively during the integration.

After the center of an accessory has been decided during the design, the following degrees and distance of an accessory based on actual integration condition can be measured. For detailed information regarding the center of the VIVE Tracker (2018), refer to guidelines related to the hardware and mechanical design.

An example of using a gun as an accessory is described in the figure below:




Figure: Example to integrate accessory and VIVE Tracker (2018)

Pitch : Angle that rotate around x axis in degrees

Yaw : Angle that rotate around y axis in degrees

Roll : Angle that rotate around z axis in degrees

D_x : Center distance of x axis between accessory and tracker

D_y : Center distance of y axis between accessory and tracker

D_z : Center distance of z axis between accessory and tracker

Content developers can collect the above information and transform Tracker pose to accessory pose.

Assume Tracker rotation matrix is $R_{Tracker}$, accessory rotation matrix $R_{Accessory} = R_{Pitch_Yaw_Roll} * R_{Tracker}$.

And accessory position $V_{Accessory} = V_{Tracker} + R_{Accessory} * Distance$

The following is a Unity sample code (reference):

```
public class Accessory : MonoBehaviour {

    const float dX = 0.0100224f;
    const float dY = -0.07616526f;
    const float dZ = 0.4884118f;

    const float roll = 10.854305f;
    const float yaw = 91.8736f;
    const float pitch = 78.805113f;

    void Update () {

        //Collect delta rotation and displacement between Tracker and Accessory
        Vector3 delta_displacement = new Vector3(dX, dY, dZ);
        Quaternion delta_rotation = Quaternion.Euler(roll, yaw, pitch);

        //Get current Tracker pose
        Vector3 tracker_position = SteamVR_Controller.Input(3).transform.pos;
        Quaternion tracker_rotation = SteamVR_Controller.Input(3).transform.rot;

        //Transform current Tracker pose to Accessory pose
        GameObject.Find("Accessory").transform.rotation = tracker_rotation * delta_rotation;
        GameObject.Find("Accessory").transform.position = tracker_position + (tracker_rotation *
        delta_rotation) * delta_displacement;

    }

}
```

Another Unity sample code shows how to transform the accessory by comparing vectors parallel to y-axis and z-axis of the VIVE Tracker (2018) (AxisY_Tracker, AxisZ_Tracker in example below) and the accessory (AxisY_Accessory, AxisZ_Accessory in example below).

```
public class Accessory : MonoBehaviour {

    const Vector3 AxisY_Tracker = new Vector3(AxisY_Tracker_X, AxisY_Tracker_Y,
AxisY_Tracker_Z);
    const Vector3 AxisZ_Tracker = new Vector3(AxisZ_Tracker_X, AxisZ_Tracker_Y,
AxisZ_Tracker_Z);

    const Vector3 AxisY_Accessory = new Vector3(AxisY_Accessory_X, AxisY_Accessory_Y,
AxisY_Accessory_Z);
    const Vector3 AxisZ_Accessory = new Vector3(AxisZ_Accessory_X, AxisZ_Accessory_Y,
AxisZ_Accessory_Z);

    void Update () {

        //Calculate delta rotation by comparing vectors parallel to Y axes of Tracker and the accessory
        Quaternion delta_rotY = Quaternion.FromToRotation(AxisY_Tracker, AxisY_Accessory);
        AxisZ_Tracker = delta_rotY * AxisZ_Tracker;
        Quaternion delta_rotZ = Quaternion.FromToRotation(AxisZ_Tracker, AxisZ_Accessory);

        //Collect delta rotation and displacement between Tracker and Accessory
        Vector3 delta_displacement = new Vector3(dX, dY, dZ);
        Quaternion delta_rotation = delta_rotZ * delta_rotY;

        //Get current Tracker pose
        Vector3 tracker_position = SteamVR_Controller.Input(3).transform.pos;
        Quaternion tracker_rotation = SteamVR_Controller.Input(3).transform.rot;

        //Transform current Tracker pose to Accessory pose
        GameObject.Find("Accessory ").transform.rotation = delta_rotation * tracker_rotation;
        GameObject.Find("Accessory ").transform.position = tracker_position + (delta_rotation *
tracker_rotation) * delta_displacement;
    }
}
```

Unity integration

This section provides an example for content developers to enable VIVE Tracker (2018) in VR content by using Unity game engine.

First, you need to make VIVE Tracker (2018) detectable in SteamVR. Assume that you have two VIVE controllers already, and you have plugged in the dongle into the dongle cradle to the computer's USB port. Right-click on one of the existing controller's icon and click "Pair Controller" in the pop-up menu (shown in figure below). Press the Power button on VIVE Tracker (2018) for 2 seconds, and then release it to enter the pairing mode.




Figure: Pair VIVE Tracker (2018)

After pairing is successful between the VIVE Tracker (2018) and the dongle, you will see that the VIVE Tracker is detected in the SteamVR UI.



Figure: VIVE Tracker (2018) is added in SteamVR

It is recommended that you use Unity 2017.3 or 2018.1 (minimum version 5.3.5) from:
<https://unity3d.com/get-unity/download>

Using the SteamVR plugin:

You need to import SteamVR Plugin into your project first. If you do not have it yet, you can download it from the Asset Store in Unity.



Figure: Unity Asset Store: SteamVR Plugin

In the developer version of VIVE Tracker (2018), it will use a similar approach and naming as you did to create content for the VIVE controller. The steps to create content for VIVE Tracker (2018) are as follows (with figures from Unity):

Step 1: Add “CameraRig” to Hierarchy to start creating content for SteamVR in Unity.




Figure: Add “CameraRig”

Step 2: Create the 3D Object for VIVE Tracker (2018). In this example, “Capsule” is used.




Figure: Create 3D Object

Step 3: Add Component > SteamVR_Tracked Object to the 3D Object “Capsule”.




Figure: Add Component “SteamVR_Tracked Object”

Step 4: Under SteamVR Controller Manager, set the size of the Objects item. In this example, one VIVE Tracker (2018) is used in the setup.




Figure: Set size of object in “SteamVR Controller Manager”

Step 5: Under SteamVR Controller Manager, on the Element 0 field, select “Capsule” as the GameObject.




Figure: Set type of object in “SteamVR Controller Manager”

Step 6: After completing the steps mentioned above, press the “Run” button in Unity. When you move VIVE Tracker (2018), you will see the Capsule object is also moving in the content.



Figure: Execution of Unity

Using VIVE Unity plugin:

You need to import the VIVE Input Utility plugin into your project first. If you do not have it yet, you can download it from the Asset Store in Unity. The VIVE Input Utility (VIU) plugin is a cross platform VR toolkit with additional support for the VIVE Trackers.




Figure: Unity Asset Store: VIVE Input Utility

Step 1: Add "ViveCameraRig" or "ViveRig" to scene Hierarchy to add support for controllers and trackers in Unity.




Figure: adding a VIVERig prefab to your scene.

Step 2. Just as with SteamVR's "CameraRig", you may remove the existing "Camera" from the scene because the rig includes a camera.

Step 3. Run to see the trackers supported just like the controllers. You will see the models from SteamVR if you also included the SteamVR plugin, otherwise you will see included models.

The VIVERig and VIVECameraRig prefabs include support for up to three trackers. To add additional trackers, simply duplicate a tracker and rename the game object. In the inspector, make sure to also update the ViveRole.

Note: Currently in both SteamVR and VIU, there is support for up to 11 (or 13, if not using controllers) from a total of 16 devices (including the hmd and base stations). Recently OpenVR has been updated to support up to 64 devices, but this has not been updated yet in the Unity plugins (but developers can add support with their own code).


VIVE Trackers and VIVE Roles

One of the benefits of using the VIVE Input Utility is that you can swap VIVE trackers or redefine where they are attached to without worrying about managing device IDs and serial numbers.

You can now assign VIVE Roles depending on the context: TrackerRole, BodyRole, HandRole and DeviceRole. For example, you can define that the same specific VIVE tracker device is always assigned to your left foot using BodyRole LeftFoot. You can also assign to trackers to the same role to make it easier to swap out tracker devices when one is low on battery.

The VIVE Input Utility also provides a tool to discover and assign roles without additional code.

There is a shortcut keyboard key, which can be assigned to display this overlay UI:



Additionally, there is an API available to create your own VR UI for assigning roles. For more information is the following article <https://github.com/VIVESoftware/VIVEInputUtility-Unity/wiki/VIVERole>. An example project is included with the VIU plugin as "7.RoleBindingExample.

Tracker on Unity or Unreal

If you encounter problems in enabling VIVE Tracker (2018) on Unity or Unreal, refer to the following links:

- For Unity 3D developers:
 - Download link for the VIVEInputUtility package: [AssetStore](#) or [GitHub](#)
 - VIVE Input Utility source code repository:
<https://github.com/VIVESoftware/VIVEInputUtility-Unity>
- For Unreal Engine 4 developers:
 - Check that you're using Unreal Engine version 4.17 or later

Firmware upgrade

Follow the SteamVR notification to update the firmware. You may also do these steps to upgrade the VIVE Tracker (2018) firmware:

1. Copy the firmware binary files (including MCU, FPGA and RF) provided by HTC into the same folder of "lighthouse_watchman_update.exe" in your PC.
2. If a VIVE controller is connected to your computer via USB, unplug it first.
3. Connect one VIVE Tracker (2018) with your computer using the USB cable.
4. Execute the following commands.

a. Update MCU's firmware:

```
lighthouse_watchman_update --target=default watchman_v3.fw
```

b. Update FPGA's firmware:

```
lighthouse_watchman_update.exe --target=default ice40_hdk_xxx.fw
```

c. Update RF's firmware:

```
lighthouse_watchman_update --target=default nrf52_xxx.fw
```

FAQs

Type	No.	Question	Answer
Common	1	How do I connect the dongle to my computer?	Connect one end of the supplied USB cable to the dongle cradle, and then attach the dongle to the cradle. Connect the other end of the USB cable to your computer.
	2	How do I charge VIVE Tracker (2018)?	<p>While in VR, you can check the battery level of VIVE Tracker (2018) when no apps are running, or when the System Dashboard is up. When the battery is low, the indicator will show a single red dot.</p> <p>Make sure to use the USB cable that's in the box. Connect the USB cable to the power adapter that came with your VIVE controllers, and then plug the power adapter to a power outlet to charge VIVE Tracker (2018). You can also connect VIVE Tracker (2018) to a computer's USB port to charge it.</p> <p>When VIVE Tracker (2018) is fully charged, its status light either shows white if it is off or green if it is turned on.</p>
	3	How do I pair the dongle with VIVE Tracker (2018)?	<ol style="list-style-type: none"> 1. Turn on the headset and pair the 2 controllers. 2. Connect the dongle to your computer. 3. Turn on VIVE Tracker (2018) to start the pairing process <p>To manually pair VIVE Tracker (2018), open the SteamVR app, tap the down arrow, and then select Devices > Pair Controller. Follow the on-screen instructions to complete the process.</p>
	4	What does the status light on VIVE Tracker (2018) mean?	<p>The status light shows:</p> <ul style="list-style-type: none"> • Green when VIVE Tracker (2018) is in normal mode • Blinking red when battery is low • Blinking blue when VIVE Tracker (2018) is pairing with the headset or dongle • Blue when VIVE Tracker (2018) is connecting with the headset or dongle • Orange when charging

	5	How can I update VIVE Tracker (2018)?	<ol style="list-style-type: none"> From your computer, open the SteamVR app. Using the supplied USB cable, connect the VIVE Tracker (2018) to one of your computer's USB ports. The firmware update will start automatically once tracker is detected by SteamVR. Warning: Do not unplug the micro-USB cable any time before the firmware update is complete. Doing so could result in a firmware error. When the update is complete, click Done.
	6	Why does VIVE Tracker (2018) automatically turn off?	<p>When VIVE Tracker (2018) turns off, some of the possible reasons might be:</p> <ul style="list-style-type: none"> The battery is drained Pairing has timed out after being idle for more than 30 seconds There was no user movement for 5 minutes
	7	Can I use more than one VIVE Tracker (2018) in a play area? What's the maximum number of trackers that can be used?	Yes. You can use a maximum of 11 VIVE Trackers (2018) plus 2 VIVE controllers in one play area.
	8	Why can't I see VIVE Tracker (2018) on SteamVR?	Check that your SteamVR app is the latest version.
	9	The Tracker button event does not work after I connected more than two devices. What can I do?	<p>You need to migrate and use the SteamVR Input System. For the latest version of the SteamVR Unity plugin that supports the SteamVR Input System, go to https://github.com/ValveSoftware/steamvr_unity_plugin/releases</p> <p>You can also use HTC's in-house integration solution from the following links:</p> <ul style="list-style-type: none"> https://github.com/ViveSoftware/ViveInputUtility-Unity/releases https://github.com/ViveSoftware/ViveInputUtility-Unity/wiki/SteamVR-Input-System-Support

Type	No.	Question	Answer
SDK	1	How do identify whether VIVE Tracker (2018) or the controller is being tracked?	You can use the class type of SteamVR SDK to identify if VIVE Tracker (2018) or the controller is currently being tracked.
	2	Does VIVE Tracker (2018) have a different coordination system compared to the controllers?	Yes. Content developers need to apply different coordination settings based on the position where the VIVE Tracker (2018) is mounted.
	3	How can I replace the controller with VIVE Tracker (2018) if I already created content meant for the controller?	Content developers need to apply different coordination settings based on whether VIVE Tracker (2018) is mounted on the same position as the controller. If its position is different, content developers need to recalibrate for VIVE Tracker (2018).
	4	What's the equivalent of VIVE Tracker (2018)'s hardware button to the controller?	The hardware button of VIVE Tracker (2018) maps to the System button of the controller.
	5	Why is tracking lost when I connected VIVE Tracker (2018) to a USB cable?	When you connect VIVE Tracker (2018) to your computer using a USB cable, it enters data sending mode that sending tracking data to computer via USB.

Type	No.	Question	Answer
Hardware	1	What is in the downloadable 3D CAD file for the VIVE Tracker (2018)?	The 1,777KB ZIP package contains the .IGS and .STP files for VIVE Tracker (2018). It is not a requirement to use the files, but it can help if you have a 3D modeling software. For details, go to http://link.vive.com/tracker/3d_model