



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Microsoft Skype for Business Deployment Guide

Configuring Skype for Business Application Endpoints

10/27/2023

Configuring Skype for Business Application Endpoints

You can configure Skype for Business application endpoints using the Management Shell.

Using the procedures described in [Microsoft documentation](#), complete the following steps:

1. Create **Trusted Application Endpoints** for Routing Points.

For example:

```
New-CsTrustedApplicationEndpoint -ApplicationId "Connector_app"  
-TrustedApplicationPoolFqdn "trustedpool.skype.lab" -SipAddress  
"sip:RP1@skype.lab" -LineURI TEL:16505551212
```

- where the value of the parameter `SipAddress` must correspond to the name of the **Routing Point DN** object in the Genesys configuration environment.

2. Create **Trusted Application Endpoints** for External Routing Points.

For example:

```
New-CsTrustedApplicationEndpoint -ApplicationId "Connector_app"  
-TrustedApplicationPoolFqdn "trustedpool.skype.lab" -SipAddress  
"sip:ERP1@skype.lab" -LineURI "TEL:14155551212"
```

- where the value of the parameter `SipAddress` must correspond to the name of the **External Routing Point** DN object (in the Genesys configuration environment) and the `<number>` in the parameter `LineURI` must correspond to the Association field of that External Routing Point object.

3. Create **Trusted Application Endpoints** for conference services.

The endpoint names must be created based on the pattern in the **uri-pattern** option and their quantity must match the **count** option set on the **Switch** object.

For example: If `uri-pattern=sip:conf{DD}@skype.lab` and `count=99`, then you must create 99 endpoints with names from `sip:conf01@skype.lab` to `sip:conf99@skype.lab`, where numbers from 1-99 are endpoint numbers.

See also how to work with [conference resource pools](#)

Trusted Application Endpoints for conference services

See [Conference Resource Pools](#) for details.